

User Manual of EATXT

Preface

This document describes how to install and use the EATXT editor. EATXT is a textual concrete syntax designed for EAST-ADL, and we have developed a matching editor for it. EAST-ADL is a domain-specific language used to describe the structure of automotive embedded systems.

In this folder, we provide EATXT in the form of source code (including its grammar definition and editor generation code). This article will introduce how to install and use it.


Prerequisites

1. You must have installed Eclipse and Java on your computer, with **Java version no less than 11**.
2. EMF is installed or You use the Eclipse Modeling Tools.
3. You must have installed Xtext for your Eclipse (You can simply install it via Eclipse Marketplace).

Installation

To use the software, you will go through the following steps:

1. Download the .zip file and extract it in your local disk.
2. Start your eclipse and import the whole project.
 - 1) In the `File` menu, choose `Import...`
 - 2) Select `Existing projects into workspace`
 - 3) Select the folder into which you cloned the source code
(Once you have imported the code, you will see a lot of errors which is normal and they will be disappeared in the later steps).
3. Reload the target definition
 - a. Find the project "org.bumble.eatxt.target"
 - b. Double click on the file "org.bumble.eatxt.target.target" to open it in the target definition editor.
 - c. In the right-top corner, click "Set as Active Target Platform"



This can take a couple of minutes. Afterwards, most of compilation errors should have disappeared and a few of them will still be remaining (This is normal, and the remaining errors will be fixed in the later steps).

Properties Problems				
32 errors, 126 warnings, 0 others (Filter matched 132 of 158 items)				
Description	Resource	Path	Location	Type
AbstractEatxtRuntimeModule cannot be resolved to a type	EatxtRuntimeM...	/org.bumble.eatxt/src/...	line 23	Java Problem
AbstractEatxtScopeProvider cannot be resolved to a type	EatxtScopeProvi...	/org.bumble.eatxt/src/...	line 51	Java Problem
AbstractEatxtScopeProvider cannot be resolved to a type	EatxtScopeProvi...	/org.bumble.eatxt/src/...	line 120	Java Problem
AbstractEatxtUiModule cannot be resolved to a type	EatxtUiModule.j...	/org.bumble.eatxt.ui/s...	line 12	Java Problem
AbstractEatxtValidator cannot be resolved to a type	EatxtValidator.ja...	/org.bumble.eatxt/src/...	line 13	Java Problem
EatxtStandaloneSetupGenerated cannot be resolved to a type	EatxtStandalone...	/org.bumble.eatxt/src/...	line 15	Java Problem
EatxtStandaloneSetupGenerated cannot be resolved to a type	EatxtStandalone...	/org.bumble.eatxt/src/...	line 26	Java Problem
Package 'org.bumble.eatxt.ide.contentassist.antlr.internal' does not exist in this plug-in	MANIFEST.MF	/org.bumble.eatxt.ide/...	line 20	Plug-in Problem


4. Generate the EATXT editor

- Open the project `src/org.bumble.eatxt` folder in the `org.bumble.eatxt` project (Please check the java version in the "Java Build Path", and it should be no lower than 17).
- Right click on the `.mwe2` file and choose `Run As` -> `MWE2 workflow` from the context menu. Because Eclipse may still display a few errors at this time, you may be asked if you want to continue. **Please click "Proceed".** (If these Java projects are using Java 11 or above in your eclipse, then you can execute this step successfully and all the errors will disappear after this step. Otherwise you may not be able to execute this step. So, please check the Build Path of each project one by one to make sure they are using Java 11 or above.)

Once you have completed the above steps, now the editor can be generated.


Common Mistakes

When you just imported the EATXT source code into your eclipse, you may see the following warning:



This is because your eclipse lacks Xtext, you should download and install it. The easiest way is to go to "Help" -> "Eclipse Marketplace..." and search and follow.

In step 4-B, the following problem is encountered:



This is usually a Java version issue. Please check your project's Build Path to make sure your project is using Java 11 or higher.

Use the EAText editor

Here, we will start the EATXT editor in runtime mode. The steps are as follows:

1. Find the project `org.bumble.eatxt`.
2. Right click on it and select `Run As` -> `Eclipse Application` in the context menu. A new Eclipse RCP instance starts.
3. click `Create a project` or `File` -> `Project` and create a generic project.
4. Create a new file with the extension `.eatxt` in the new project. On double click, it opens in the EATXT editor.

5. Alternatively, import the `org.bumble.eatxt.example`` project into your runtime Eclipse RCP and we have provided two files there, i.e., `example.eatxt` and `example.eaxml`.

(the project `org.bumble.eatxt.example`` is in the folder “examples”)

You can right click on the file and click "Convert to ..." to serialize EATXT model to EAXML or the other way round.