
Picoloop Manual



Picoloop Tutorial (PocketChip version)

Welcome to Picoloop!

Picoloop is a synth and a step sequencer made by Yoyz. In this tutorial, we'll make a tour of the basic functionalities of **Picoloop**. The commands described here are adapted for the usage on PocketChip.



Contents

Picoloop Tutorial (PocketChip version)	
Starting	ii
Entering notes	٧
Saving and loading music	i
Exploring new horizons	X
Picoloop Memo (PocketChip version)	χV
	XV
Other commands	χiχ

i

Starting

First, get **Picoloop** at https://github.com/yoyz/audio/

Compile it yourself, if needed (instructions are provided in the readme). You can also tweak some parameters, found in the Master.h file, before the compilation, such as the MAX_PATTERN_BY_PROJECT variable to increase the pattern slots. The Windows and PSP binaries can be found in the Releases tab.

The requirements for starting the application are:

- The picoloop binary itself (called "picoloop" or "PatternPlayer_#####" after you've just compiled it, you can rename it if needed)
- the font.ttf file
- optionnally the patch/MDADrum/ folder if you want to get some electronic drums
- the bank/ folder to store your creations.


Run the **Picoloop** binary. You will be presented to a setting panel. Navigate with \leftarrow , \rightarrow , \uparrow and \downarrow and choose the color theme (palette) you prefer.

Then make sure the AudioOutput matches your soundcard. Eventually make it select and display "default".

```
Current Bank : 0
> AudioOutput : 1/1 : default
MidiOutput : 0/1 : Midi Through 14:0
MidiInput : 0/2 : Midi Through 14:0
MidiClockMode : Internal
```

To exit this panel and start making music, validate with Right Shift. In the case it crashes, it might be because the soundcard configuration was not correct. Restart the binary and select another card setting.

You will be presented to the **Picoloop** main window.




With this color scheme, the 16 steps are in light grey. The moving dark grey cursor is the current sounding note. The cursor for edition is in white and you cannot move it right now (you're in *Menu mode*). Below the 16 steps is the menu. It displays:

[ENV] Note OSC VCO LFO FLTR

Move left or right to select the parameter you want to use.

At the moment, select Note with the Right Ctrl key. Now you are in *Edit mode*, and you can navigate within the 16 steps with the \leftarrow , \rightarrow , \uparrow and \downarrow arrows. Insert your first note with the Right Shift key. It will be a C2.


You can change the value of this note by holding Right Ctrl and typing on the arrows. ← or → for decreasing or increasing 1/2 tone, ↑ or ↓ for increasing or decreasing 1 octave. Make it for example G2. Now select other empty cases and type Right Shift for adding more notes and Right Ctrl for changing their values. Delete an existing note with Right Shift. The next note entered with Right Shift will be the previous value which was deleted (delete an A3, next one with be A3 then).



There are 4 tracks which can play together. To change the current working track, go back to the menu with the ESC key. Use the ↑ and ↓ arrows to select the track. It will display Track/0, Track/1 etc. Now you can enter more notes in this other track.

To change the sound of the current notes, select ENV in the menu, and validate with Right Ctrl, the menu will disappear, meaning you can enter notes or change values. In the ENV parameters, you can alter the sound with Right Ctrl + arrows. Try to play with the two

parameters. You end up with something like that:



Now if you type the Enter key, you'll access more parameters, which you can change in a similar way. In this mode, you alter parameters for individual notes, if you want to change all the inserted notes for the current track, exit the *edit mode* with the ESC key, and use Right Shift + arrows to change all the steps together.

Saving and loading music

Now it's time to save your first work!

Exit the *edit mode* with ESC if you're still in it, and type again ESC to enter the second menu (*Menu2*).

It will display:

L/S [BANK] PSH MAC FX BPM

Select L/S (*Load/Save*) and enter the menu with (Right Ctrl).

It will look like this:

This screen is for saving individual patterns, but also to organise them into a whole song.

The menu on top represents your tracks. The cursor on this screenshot is on the top 0E column. To save an individual track, select an empty slot and type $\overline{\text{Right Ctrl}} + \downarrow$. Now the slot will be lighter (with this grey theme). To save all the 4 tracks (one pattern), type $\overline{\text{Right Shift}} + \downarrow$, the whole column will be lighter.

To reload you tracks later, select a column and type $\overrightarrow{Right Shift} + \uparrow$. To load an individual slot, type $\overrightarrow{Right Ctrl} + \uparrow$. Beware, there is no warning so it might erase your current work.

Now you can assemble your tracks with the order list (under the Song Position label). Go into this list with the Enter key.

You can define Loop start position with $\boxed{\text{Right Shift}} + \uparrow$. As soon as you define this, the song with start to play. And you can define Loop end position with $\boxed{\text{Right Shift}} + \downarrow$.

Change the values of the list with Right Ctrl $+ \uparrow / \downarrow$

Important:

- 1. When you're in the order list, your changes are saved only when you exit it to the pattern editor with ESC. If you close **Picoloop** before doing this, your changes won't be saved!
- 2. When you're in the pattern editor, the data are written in a buffer, and you must save the current pattern in the track grid before playing your song from the order list (otherwise the changes in the pattern won't be saved). You can only save the pattern in the same row as the pattern number you've worked in. For example a pattern in the Track/1 can only be saved in the second row in the track grid (tracks are starting from 0, Track/0 is the first one, Track/1 is the second one)

Each bank is for storing a different project (=song).

There is no option for backing up a bank you're working on, so it can be a good idea to backup your whole bank/ folder from time to time. On Linux / Unix systems, you can use a script like this from the command line:

zip -r bank_picoloop_'date +%Y-%m-%d_%H:%M'.zi

To record your music, you can either (obviously) plug a recorder to the line-out of your computer or device, but you can also set this environment setting before starting picoloop:

export DUMP_AUDIO=1 && picoloop

Exploring new horizons

As we've seen earlier, we can change the pitch value (note) of a step, but also some parameters such as ENV (enveloppe), OSC (oscillator), VCO (a kind of mixer), LFO and FLTR (filter). If you press Enter while in a

parameter menu, you can also get more parameters related to the first one (for example in the ENV menu, you'll get first Attack/Release, and after pressing Enter you'll get Decay/Sustain, one more press on Enter and it's Trig/Amplification). Note: on some engines, ENV is replaced by A/R.

But we can also change the whole engine, using the "MAC" menu in *menu2*. The different engines are (from up to down):

- Psynth (default): PicoSynth, soustractive synth with 2 oscillators (lightweight).
- SID: emulation of the MOS SID 6581/8580 soundchip (found on Commodore C64 8-bit computers), based on the resid engine
- Mdrum: MDA Drumsynth (you need the patches in the picoloop/patch/MDADrum/ folder)
- Mdiout: midi out
- Tsynth : Twytch/Helm. Needs high ressources.

- 0303: based on Open303, a free, open source emulation of the Roland TB-303 synthesizer. Needs high ressources.
- Csynth: Cursynth, a soustractive synth with 2 oscillators. Needs high ressources.
- PBS: PBSynth, another soustractive synth with 2 oscillators (lightweight).
- Pdrum: Picodrum, for making rythms (kicks, hats, snares...)
- OPL2: FM synthesis
 On some less powerful machines, the high ressources engines are not enabled.

Refer to the picoloop README for all the parameters or experiment yourself.

Picoloop Memo (PocketChip version)



Menu mode		
\leftarrow / \rightarrow	move backward/forward in	
	the menu	
↑ / ↓	select the track from 0 to track	
	3	
Right Ctrl	do nothing	
	edit all step at once	
(Right Shift)	enter the edit mode	
TAB	go to the next 16 step on the	
	same track	

XV

Backspace	go to the previous 16 step
	the same track
ESC	call menu2 or menu1

Edit mode	
\leftarrow / \rightarrow	select next step
↑ / ↓	select step+4, step-4
(Right Ctrl)	enter a note in a step, it wor
	a cut/paste
$\boxed{ \text{Right Shift)} + \leftarrow / \rightarrow / \uparrow / \downarrow }$	edit the current step
Right Shift	do nothing
TAB	go to the next 16 step or
	same track
Backspace	go to the previous 16 step or
	same track
ESC	call menu2 or menu1
Enter	cycle between the differen
	rameters

ΧVİ

L/S menu

Bank			
Right Ctrl) + ↓	Save the current track on the		
	selected slot		
Right Shift) + ↓	Save your current pattern		
	(group of 4 tracks)		
Right Ctrl) + ↑	Load a track (replace cur-		
	rent)		
Right Shift + ↑	Load a 4 tracks pattern		

Song position (order list)	
Right Shift) + ↑	Define Loop start
	position
Right Shift) + ↓	Define Loop end
	position
Right Ctrl) + ↑/↓	Change the values

$\boxed{ (Right Ctrl) + \leftarrow / \rightarrow}$	сору	value	left or
	right		
	insert	or	delete
	value	(shif	t pat-
	terns)		

PSH menu			
Right Shift)+↑	Increase the track		
	size (16 steps block)		
Right Shift)+	Decrease the track		
	size (16 steps block)		
$ \overline{ (Right Shift)} + \rightarrow $	Increase the track		
	size (1 step)		
Right Shift)+←	Decrease the track		
	size (1 step)		
(TAB) and (Backspace)	Navigate into the		
	new steps (-16 or		
	+16)		

Other commands

Volume	
ESC)+↑	Increase volume
ESC)+↓	Decrease volume

Get picoloop at https://github.com/yoyz/audio/

Made by Garvalf (http://garvalf.online.fr) with the textallion word processor and the txt2tags syntax.