



MidiEditor

(User Manual)

Markus Schwenk ©




MidiEditor




Contents


1) Introduction	3
2) Midi – A Short Overview.....	4
2.1) Tracks and Channels.....	4
2.2) Midi Events	5
2.3) Midi I/O	6
3) The Editor and its Components.....	7
3.1) Menu bar	7
3.1.1) File Menu.....	8
3.1.2) Edit Menu	8
3.1.3) Tools Menu.....	9
3.1.4) View Menu	12
3.1.5) Playback Menu	12
3.1.6) Midi Menu	13
3.2) Tool bar.....	14
3.3) Event View	14
3.4) Track Editor.....	14
3.5) Channel Editor	15
3.6) Event Editor	15
4) Setting up MidiEditor	17
4.1) Midi I/O	17
4.2) Making the Input Device audible.....	17
4.3) Starting Synthesizers along with MidiEditor	18
4.4) Automatic Updates	18
4.5) Support for Older Devices	18
4.6) Larger Playback Toolbar	18
5) Editing Midi Files	20
5.1) Selecting Events	20
5.2) Moving Events	20




MidiEditor



5.3) Changing the duration of Events	21
5.4) Creating and deleting Events.....	21
5.5) Standard Tool.....	22
5.6) Magnet and Raster.....	22
5.7) Quantization	22
5.8) Copying/Pasting Events.....	23
5.9) Editing Tempo and Meter.....	23
5.10) Add or Remove Measures	23
5.11) Editing Controls and Velocities	24
5.12) Tracks and Channels.....	24
5.13) Tweaking Event Properties.....	25
6) Playback	26
6.1) Muting Tracks and Channels	26
6.2) Setting the Cursor	26
6.3) Speed	27
6.4) Metronome.....	27
6.5) Locking the Screen	27
7) Recording Midi Data	28



MidiEditor





1) Introduction

[MidiEditor](#) is free software providing an interface to edit, record, and play Midi data. The editor is able to open existing Midi files and modify their content. New files can be created and the user can enter his/her own composition by either recording Midi data from a connected Midi device (e.g., a digital piano or a keyboard) or by manually creating new notes and other Midi events. The recorded data can be easily quantified and edited afterwards using MidiEditor.

This manual will provide an overview over the many different features of MidiEditor. However, as it would go beyond the scope of this manual to discuss the foundations of Midi, only a quick overview will be provided here.

Note: MidiEditor was developed by Markus Schwenk. It is entirely written in C++ (Qt) and is available for the platforms Linux and Windows. Should MidiEditor be software which is helpful for you and which you use often please let the developer and other users know by providing feedback. Moreover, the developer worked on MidiEditor in his (rare) spare time and offers it for free. So, when you feel like it, pay him a coffee (or two). Please also feel free to contact the developer in case you have any ideas which could help to improve the editor or in the case you found any bugs you want the developer to fix.





2) Midi – A Short Overview

Midi (Musical Instrument Digital Interface) is a digital interface allowing the user to control virtual music instruments on his computer or on other hardware components. In general, the Midi protocol is used to exchange commands like "play note X with velocity Y on instrument Z" or similar.

Those commands are usually stored and exchanged using so-called Midi events. They can contain information about the notes which are currently played, the sounds which belong to each (virtual) instrument, or general information about the song, e.g. about the key, the meter, or the song's name. While the above mentioned commands are definitely the most often used, there are many other commands, which can e.g. control the sustain pedal of a piano or define an instrument's overall volume. The events are presented below in more detail.

2.1) Tracks and Channels

The different virtual instruments are organized in tracks, where each track refers to one instrument or a group of instruments. Hence, each Midi event is assigned to a track. Each note will be assigned to the track of the instrument which plays the note, while events, which do not belong to a specific instrument (key, meter, etc.), are usually assigned to a specific track ("Tempo Track"). Moreover, each note and other instrument-specific events are assigned to a channel. There are 16 channels where each channel has a defined sound (e.g. "Piano" or "String Ensemble"). While it may sound redundant to have each note assigned to a track and a channel, the concept makes sense. This is, because the information about the different tracks is only known to the device requesting another device to play the note. The other device will only receive information about the channel on which to play the note, which reduces the traffic needed to exchange the information. Hence, the tracks are (mostly) for a user's orientation when editing a file. Usually, all notes within a single track are also assigned to one specific channel. However, there are exceptions, e.g. when a group of strings is divided into two parts where one part plays pizzicato and the other part plays legato; in this case both groups can be noted in the same track but they have to use different channels, as each group has another sound.



2.2) Midi Events

The following list shows the different Midi events and provides an overview of their functionality.

- *Note On/Off Events*

Each note is represented by two events, where one event indicates the start of a note and the other event is used to stop the note. The note height is represented by a number from 0 (C0) to 127 (G10) and the note's velocity (loudness) has a range from 0 to 127. The note is assigned to a channel, where the channel's configuration specifies the voice of the note.

- *Tempo Change Events*

A Tempo Change Event sets the current tempo. The tempo is set in beats per minute (BPM). Higher values indicate a faster tempo.

- *Time Signature Events*

Any meter change is represented by a Time Signature Event in Midi. The event holds two parameters, the numerator and the denominator of the meter. E.g., in order to represent an *alla breve* meter, the numerator would be set to 2 and the denominator would be set to half notes.

- *Key Signature Events*

A Key Signature Event defines the song's key (*C major, G minor, ...*).


- *Program Change Events*

In order to define the voice (or instrument) assigned to each channel, a Program Change Event can be used. E.g., after the program *Church Organ* has been set for channel 5, all notes played on channel 5 will be played with an organ's voice.


- *Control Change Events*

Besides the voice assigned to each channel, a lot of other properties regarding a channel's sound can be controlled using Control Change Events. Up to 128 different controls exist for each channel where a value between 0 and 127 can be assigned to each control. The available controls include the sustain pedal of a piano, the channel's overall volume, and the modulation wheel.

- *Key/Channel Pressure Events*



MidiEditor



These events control the pressure for each note (Key Pressure Events) or for all notes played on a given channel (Channel Pressure Events).

- *Pitch Bend Events*

The Pitch Bend Events are used to modify the pitch of a given channel.

- *Text Events*


Lyrics, instrument/track names or general information (Copyright etc.) can be stored in Text Events.

- *System Exclusive Events*


System Exclusive Events are used by manufacturers to provide a way to send device-specific messages.

2.3) Midi I/O

While synthesizers can easily be installed and run on a computer, a lot of hardware exist which can be used to play or record Midi data (e.g. digital pianos or hardware synthesizers). Such additional hardware is usually connected to the computer using a USB port. Whether or not a synthesizer or a keyboard is running on a computer or an additional hardware which is connected to a computer does not affect the way how the device is used within Midi software (e.g. MidiEditor). In both cases, a Midi port will exist for each device to allow the software to receive data from or to send data to the device.




MidiEditor



3) The Editor and its Components

The following screenshot shows the editor in use:



On the top of the editor there are the menu bar and the toolbar which contain buttons to load and save files, to play the currently loaded file, or to edit the file's content. Moreover, the settings can be accessed from the menu bar and additional tools, such as the metronome, can be controlled from the menus.


Below the toolbar, the main screen is split into two parts. On the left side, there is the event view, which shows all events, and a view which can be used to visualize and edit the velocity for each note as well as the different controller values, the pitch for each channel, or the key/channel pressure.

On the right side, there are different windows allowing the user to edit the tracks and channels, to visualize the protocol of all actions the user did, and to edit all properties of the selected event(s).


3.1) Menu bar

Most actions which can be performed by the user are accessible using the menu bar. The actions are structured within the following sub menus:

File The [file menu](#) provides the usual actions to load, create, and save files.



MidiEditor



- Edit** The [edit menu](#) provides actions to select events, to copy and paste events, and to undo / redo actions.
- Tools** The [tools menu](#) provides actions to edit the current file's content.
- View** The [view menu](#) provides actions to customize the view settings. This includes items to zoom in or out and the raster settings.
- Playback** The [playback menu](#) contains all actions which control the playback, the recording, or the metronome.
- Midi** The [Midi menu](#) provides actions which let the user set the Midi preferences.

3.1.1) File Menu



New

Creates a new, empty Midi file.



Open...

Open an existing Midi file.

Open recent...

Open an existing Midi file from a list of recently opened files.



Save

Save the current Midi file.



Save as...

Save the current Midi file at a given path.

Quit

Close MidiEditor.

3.1.2) Edit Menu



Undo

Undo the last action.



Redo


Redo the last action which has been undone.

Select all


Select all events which are currently visible.

Select all events from channel...

Select all events which are assigned to a given channel.



MidiEditor



Select all events from track...

Select all events which are assigned to a given track.



Copy events

Copy all selected events to the clipboard.



Paste events

Paste the copied events from the clipboard. The first event will start at the cursor position. Using the paste options (see below) the user can specify which track and channel the new events will be assigned to.

Paste options...

Lets the user specify, which channel and which track pasted events will be assigned to. Fixed tracks and channels can be chosen, or the channel and track from the copied events can be chosen. Also, the channel and track which have been chosen for new events can be selected.



Settings...

Opens the settings dialog (see [Setting up MidiEditor](#))

3.1.3) Tools Menu

Current tool...

This menu contains a list of all available tools which can be selected for editing the file's content inside the event view (see below for details of the individual tools).



Standard tool

The [standard tool](#) combines all tools and is able to perform most actions needed to edit Midi data.



Select single Events

This tool can be used to [select or deselect](#) single events.



Select Events (Box)

This tool can be used to draw a box around events to [select or deselect](#) them.



Select all Events on the left side

[Select](#) all events occurring before a given time.




Select all Events on the left side

[Select](#) all events occurring after a given time.














Move Events (all directions)


[Move](#) all selected events in both directions.




MidiEditor



-  *Move Events (Left and Right)*
[Move](#) all selected events left and right.
 -  *Move Events (Up and Down)*
[Move](#) all selected events up and down.
 -  *Change the duration of the selected event*
[Change the duration](#) of all selected notes.
 -  *Create new Events*
[Add new events](#) to the file.
 -  *Eraser (remove events)*
[Remove events](#) from the file.
 -  *Remove selected events*
[Remove](#) all currently selected events.
 -  *Align left*
Makes all selected events start at the same time. This time is equal to the start time of the leftmost selected event.
 -  *Align right*
Makes all selected events end at the same time. This time is equal to the end time of the rightmost selected event.
 -  *Equalize*
Makes all selected events have the same duration as well as the same start and end times. The new duration is equal to the average duration of the selected events.
 -  *Quantify selection*
Quantifies all selected events. After quantization, the events will have exact note lengths (quarters, 8ths etc.). Also their timing inside the measure will be exact. The smallest fraction (i.e. the smallest duration of the notes) can be specified using the menu "Quantization fractions" (see below). [Click here for details](#)
- Quantization fractions*
Set the smallest note duration for the quantization. [Click here for details](#)
- Quantify tuplet...*
As tuplets cannot be quantified with the above explained tools, select the notes which belong to the tuplet and click "Quantify tuplet...". A dialog will popup which lets you enter details for the tuplet quantization. [Click here for details](#)
- Repeat tuplet quantization*



MidiEditor



Select the notes belonging to a tuplet. Click this menu item in order to quantify the tuplet with the last entered properties (using the menu item above). [Click here for details](#)

Add track

Adds a new, empty track to the Midi file. [Click here for details](#)

Remove events from channel...

Removes all events which are currently assigned to a specified channel. [Click here for details](#)

Move events to channel...

Assigns all selected events to the specified channel. [Click here for details](#)

Move events to track...

Assigns all selected events to the specified track. [Click here for details](#)

Transpose selection...

Transposes selected events up or down, based on semitone numbers entered by the user in the opening dialog.

Set file duration

Set the song's duration in milliseconds. If the entered duration is smaller than the current duration, everything beyond the new end of the file will be removed.

Scale events

Scales the timing of all selected events.



Magnet

Enables or disables the magnet. The magnet can be used to align moved, scaled, or newly created events to the specified raster. [Click here for details](#)



Edit Tempo

Allows changing the tempo within a song. [Click here for details](#)





Edit time signatures

Allows changing the meter within a song. [Click here for details](#)



Add or remove measures

Allows the user to add or remove measures. [Click here for details](#)



3.1.4) View Menu

Zoom...

This menu contains items which allow you to zoom in or out (horizontal and vertical) and to restore the default zoom settings.



Show all channels

Sets all channels to visible.



Hide all channels

Hides all channels. Events from hidden channels will not be shown in the event view.



Show all tracks

Sets all tracks to be visible.



Hide all tracks

Hides all tracks. Events from hidden tracks will not be shown in the event view.

Colors...

Provides two items which let the user select whether the events' colors shown in the event view are obtained from the events' channels or from their tracks.

Raster

The raster shown in the event view ([click here for details](#)) can be customized with this menu. The raster can be turned off or set to the known note lengths (i.e. quarters, 8ths, etc.).

3.1.5) Playback Menu



Play

Plays the song from the selected [cursor](#) position. [Click here for details](#). In order to make your songs audible, make sure that an [output device is specified](#).



Pause

Pauses the playback.



Record

Records data from the [input device](#). [Click here for details](#).




Stop


Stops the current playback or the current recording.



Back to begin



MidiEditor



Moves the [cursor](#) to the beginning of the song.



Previous measure

Moves the [cursor](#) back to the beginning of the previous measure.



Next measure

Moves the [cursor](#) forward to the beginning of next measure.

Playback speed...

Provides a menu which allows the user to select a playback speed. This will speed up or slow down the playback. [Click here for details.](#)



All channels audible

Makes all channels audible during playback. [Click here for details.](#)



Mute all channels

Mutes all channels during playback. Notes from channels which are not audible will not be played during playback. [Click here for details.](#)



All tracks audible

Makes all tracks audible during playback. [Click here for details.](#)



Mute all tracks

Mutes all tracks during playback. Notes from tracks which are not audible will not be played during playback. [Click here for details.](#)



Lock screen while playing

If checked, the window will not be updated during playback. This is useful if the update should causes delays. [Click here for details.](#)



Metronome

Enables or disables the metronome. [Click here for details.](#)

3.1.6) Midi Menu



Settings...

Opens the settings dialog (see [Setting up MidiEditor](#))




Connect Midi In/Out


If the connected [input device](#) does not make the notes audible which are played on this device (e.g. during recording), it can be made audible by connecting it to the specified output device. [Click here for details.](#)

Midi panic

Sends a Midi panic signal to the [output device](#). This device is expected to be silent after this signal.



MidiEditor



3.2) Tool bar


The toolbar contains items from the menu bar in order to provide quick access to the most frequently used actions.

3.3) Event View

The event view is the most important part of the editor. It visualizes the events in the loaded Midi file. Moreover, most editing can be done in this window.

All events are colored, where the colors can either be chosen to represent the event's channel or its track.

Notes are displayed as bars. The rows of the event view represent the different notes according to the piano roll on the left. The horizontal length of a note represents the note's duration according to the time line on the top of the window.





Below the notes the other events are shown. The row names below the piano roll indicate the event type shown in each row.

In order to [edit](#) the content of a Midi file, the user has to select a [tool](#) in the menu bar or in the toolbar. After that, the user can select events in the event view and move the events, change the notes' durations, create new events, and remove events.


Below the event view, the velocities of all notes, the controllers, the key/channel pressure, and the pitch of each channel can be [edited](#) and visualized. The user can select the data to show and edit on the left of the window.





3.4) Track Editor






MidiEditor






The track editor contains a list of all tracks in the currently loaded Midi file. The list shows the names of the tracks as well as their numbers and the tracks' colors. Moreover, the track editor enables the user to hide or mute specific channels (by clicking  and ), to rename a track (by clicking ) or to delete a track (by clicking ).


New tracks can be added to the Midi file by clicking  .

In order to mute or hide all tracks at once, the according actions above the track list can be used.

Please refer to [Tracks and Channels](#) for more details about the track editor.

3.5) Channel Editor

Similar to the track editor, a list of all channels is provided in the channel editor. Channels can be hidden or muted (by clicking  and ). Moreover, the solo mode (by clicking ) can be activated for a specific channel which will make the channel be the only audible channel until the solo mode is deactivated.


As an instrument (or "voice") is assigned to each channel at each time, the channels' instruments can be assigned by clicking  . This will open a dialog which lets the user specify the instrument for the given channel.

Please refer to [Tracks and Channels](#) for more details about the channel editor.


3.6) Event Editor

Once one or more events have been selected, the events' data will be visualized inside the event editor. The data is provided as a table containing property-value pairs. Double-clicking inside any value-field will allow the user to modify the property's value which will set the new value to all selected events immediately.


Protocol	Event	
Property	Value	
Type	Note On/Off Event	
On Tick	576	
Off Tick	768	
Duration	192	




MidiEditor



In the case of multiple selected events, the editor will only show the values which are equal for all selected events. Assigning new values to those initially empty values will set the value for all selected events.




MidiEditor



4) Setting up MidiEditor

4.1) Midi I/O

MidiEditor has to be correctly configured in order to be able to send data to a Midi device which is connected to the computer and (if required) to receive any data in order to allow [recording](#). If not correctly configured, MidiEditor can be used to edit Midi files; however, you won't be able to listen to the music.



To select the input or output device click "Settings.." in the [midi menu in the menu bar](#). In the list on the left-hand side of the upcoming dialog, please select the card "Midi I/O". This will show two lists which show all available input/output devices.


Select in-/and output from the lists and click "Close".

On startup, MidiEditor will always try to connect to the devices which have been used during the last session.


4.2) Making the Input Device audible



A lot of Midi devices which allow you to input Midi data are not audible but need a connected computer to generate sounds (similar to MidiEditor). When having chosen a valid output device, you can pass all notes



MidiEditor



played at the input device to the output device which makes the played notes audible. Select the option "Connect Midi In/Out" in the [midi menu in the menu bar](#) or in the toolbar.

4.3) Starting Synthesizers along with MidiEditor

There are a lot of synthesizers MidiEditor can use to produce its sound with. However, some of those synthesizers have to be started each time you start MidiEditor, as they are not running by default.

To start software each time when MidiEditor is started, you can set a start-command which is executed at each startup of the editor. To enter this command, click the menu entry "Settings..." in the [midi menu in the menu bar](#). Select the card "Additional Midi Settings" and enter your start command in the according field. The output of the started component will be visible (after the next startup) in the text area below this field.

4.4) Automatic Updates

MidiEditor connects to internet at each startup in order to check whether a new version of MidiEditor is available. If so, you will be notified and asked to download the new version.


In order to make sure, that MidiEditor can connect to the internet configure your firewall accordingly. To disable the automatic update checker, please open the settings dialog, chose the card "Updates" and deselect the checkbox.

4.5) Support for Older Devices


Some old Midi devices may not support the full Midi instruction set. Hence, these devices may not stop the currently played notes when you click the stop button. MidiEditor provides a solution for this, which can be activated in the "Additional Midi Settings" card in the settings dialog. In order to activate it, check the checkbox "Manually stop notes". This should not be used when your Midi device does stop the playback whenever requested.

4.6) Larger Playback Toolbar


MidiEditor allows you to start with a larger playback toolbar. This is necessary when using the editor while being seated at your digital piano. The editor has to





MidiEditor



be started along with the command-line argument `--large-playback-toolbar`. On Linux, use the command line to start MidiEditor. On windows, right-click on the desktop-shortcut and select "Properties". Add the argument `--large-playback-toolbar` to the target field as shown below.





5) Editing Midi Files

5.1) Selecting Events

In order to edit Midi events, the events which will be edited have to be selected. There are many different ways how to select events. Events can be selected using the [standard tool](#) or using one of the tools listed below.

When pressing SHIFT while selecting events, the old selection will be extended with the newly selected events. In order to remove events from a selection, the events can be accessed as if you wanted to select them while pressing CTRL.



Select single Events

Click on an event in the view to select it.



Select Events (Box)

If you want to select more events at the same time you can use the "Select Box" Tool. Click at any point in the event view and drag the appearing box. All events in the box will be selected.



Select all Events on the left side

Select the tool and click at the wished horizontal position. All events before the clicked position will be selected.



Select all Events on the right side


Select the tool and click at the wished horizontal position. All events after the clicked position will be selected.

When pressing CTRL+A, all visible events will be selected. Moreover, events from a specific track or from a specific channel can be selected using the according actions in the [edit menu in the menu bar](#).


Once an event has been selected, you can navigate the selection to nearby events using the arrow keys on the keyboard.

5.2) Moving Events

Moving events will either change their start- and end- times (horizontal movement) or the note height of note events (moving notes up and down). While the [standard tool](#) can select and move events at the same time, selected



MidiEditor



events can either be moved with one of the tools listed below, or by accessing the according values of the events in the [event editor](#).

✚ *Move Events (all directions)*

Click inside the event view and drag the mouse in order to move all selected events.

↔ *Move Events (Left and Right)*

Click inside the event view and drag the mouse in order to move all selected events horizontal.

↑↓ *Move Events (Up and Down)*

Click inside the event view and drag the mouse in order to move all selected events vertical. This tool only works with note events.

Moreover, the timing of the events can be corrected by [quantifying](#) them.

5.3) Changing the duration of Events

↔ Resizing note events changes the start or the end time of the event - this means the duration of the note. All other events cannot be resized. The duration of a note can either be directly set using the [event editor](#) or by selecting the resizing tool (shown on the left). To use the tool, select the events to resize and move the mouse over the start or the end of a selected event. Drag the mouse in order to resize the event. The [standard tool](#) can also resize events.

5.4) Creating and deleting Events



✎ Creating events can be done with the [standard tool](#) or with the new events tool (shown on the left). Clicking inside the event view and dragging the mouse will create the events. New events will be assigned to the track and the channel which are defined in the lower right corner of the editor.

Add new events to ...

Track: Track 1: New Instrument


Channel: Channel 2

In order to remove events, you can press the DEL key which will delete all selected events. Moreover, events from a specific channel can be removed by




clicking the according action in the [tools menu](#). The remove events tool can remove specific events.


5.5) Standard Tool

 This tool is the most often used tool in MidiEditor. It provides a mixture of all selectable tools above. Events can be selected by clicking on them or by dragging a box around the events to select. In order to add an event to an already existing selection, hold the SHIFT key while selecting new events in the above explained manner. In order to remove individual events, hold CTRL and click on the events to deselect. Events can be moved up and down as well as left and right by clicking inside the event and dragging the mouse. Clicking at the left or right border of an event and dragging the mouse afterwards will change the duration and the starting time of the event. All actions will be applied to all selected events. Clicking the right mouse key will create new events.


5.6) Magnet and Raster

 When the magnet (shown on the left) is enabled, all dragging or shifting operations inside the event view will result in a timing which is aligned to the specified raster. That means that events will start at the correct time when the start time is close to the time which is represented by a vertical line in the event view. The raster size can be controlled from within the [view menu in the menu bar](#). It can be set to any known note length (eighths, quarters etc.).



5.7) Quantization

 While an event can start and end at any time, it is often required to make the timing "correct" which means, that the event starts at an exact position within the measure and have a duration which is equal to a known note duration (quarter, 8th, ...). This exact timing can be achieved by quantifying the events. Pressing the quantify button (shown on the left) will align all selected events to a grid. The size of this grid, the quantization fractions, can be controlled from within the [tools menu in the menu bar](#).

The following picture shows some notes before (left) and after (right) quantization. The quantization fractions were set to 8ths.



MidiEditor



As tuplets are not aligned on the usual grid, you can select the events which belong to a tuplet and use the action quantify tuplet in order to correct a tuplet's timing.

5.8) Copying/Pasting Events

In order to copy events, select the events to copy and press CTRL+C. This will copy the events to the clipboard. Set the [cursor](#) at the time where you want the copied events to start and press CTRL+V which will paste the events at the wished position.

5.9) Editing Tempo and Meter

Tempo and meter can be changed using the according tools. Tempo can also be changed using the [control editor](#) below the event view.



Edit Tempo

After selecting the tool, click inside the event view at the position where you want to change the tempo. A dialog will pop up letting you enter the new tempo.

You can also select a time period by letting the mouse pressed after clicking and moving the mouse to the end of the time period. This allows you to gradually increase or decrease the tempo.



Move Events (Left and Right)



Click inside the event view and drag the mouse in order to move all selected events horizontal.

5.10) Add or Remove Measures




Add or remove measures

Either click on the line between two measures to add measures, or select a single or multiple measures and press the DELETE key on your keyboard to remove the measures.



5.11) Editing Controls and Velocities

Below the event view there is a window which allows you to edit and visualize the control change events, the velocity of the notes, and other parameters.



Editing can be done with three different modes:



Single mode

The curve's points can be selected and dragged. New points can be created by clicking areas with no points.



Free-hand mode

A freehand curve can be entered by moving the mouse while pressing the left button.






Line mode


A line can be dragged with the mouse.


5.12) Tracks and Channels

Each Midi file separates its events in one or more tracks. Each track can contain multiple channels.



Each track has a name. This name describes the tracks content. To change it you can press the button  in the [track editor](#). A dialog will open up to enter the tracks new name.

To create a new track you can press the button  in the [track editor](#). To remove a whole track you can press . This will delete all events of the selected track and the track itself. If there is only one track left, this track cannot be deleted.

Channel 0 - 15 are the instrument channels. They contain information about the notes to play and the instruments sound. The sound of the instrument can be chosen from a list of instruments. Press  in the channel list to change the instrument. This will open up the following dialog:



MidiEditor



You can specify the instrument from the given list. Accepting the dialog will set the channel's instrument in the beginning of the file to the instrument from the list. Later in the file there may be Program Change Events changing the channel's instrument. To prevent this, you can select "Remove other Program Change Events" before accepting the dialog. All other Program Change Events of the channel will be removed.



5.13) Tweaking Event Properties

You can finely tweak the properties of selected events using the keyboard. First choose which property to tweak:

- Time, preserving duration = 1
- Start time = 2
- End time = 3
- Note = 4
- Note velocity, controller value, or tempo = 5

Then choose how you'd like that property of the respective selected events to be modified:

- Small decrease = 9
- Small increase = 0
- Medium decrease = Alt + 9
- Medium increase = Alt + 0
- Large decrease = Alt + Shift + 9
- Large increase = Alt + Shift + 0




6) Playback

MidiEditor allows you to play the song when you have selected an [output device](#).

You can find buttons for the playback in the [playback menu](#) or in the toolbar. There are buttons which allow you to start a playback (or a recording, please read [Recording Midi data](#) for more details), to stop and pause the playback, and to control the [cursor](#). Moreover, individual tracks and channels can be muted and the [metronome](#) can be controlled from within the [playback menu](#).

6.1) Muting Tracks and Channels

Sometimes it makes sense to play only specific channels or tracks in order to listen to one or more instruments at a time. Hence, specific tracks and channels can be muted. If either the track or the channels assigned to a Midi event is muted, the event will be ignored during the playback. Hence, notes of muted tracks and channels will not be audible during the playback.






In order to mute a specific track or a channel, please press  in the according list in the [track editor](#) or the [channel editor](#). Click again in order to make the channel or track audible again.




Moreover, there are actions which allow you to mute or make audible all tracks or channels at once. These buttons can be found in the [playback menu](#) as well as in the [track editor](#) or the [channel editor](#).

If you want to play one channel alone, the channel can be marked to be the "solo channel". This will automatically mute all other channels without having to mute them manually. The solo mode can be entered by clicking S for the according channel in the [channel editor](#).

6.2) Setting the Cursor

You can specify the position in the song where the playback starts when pressing the play button. This can be done by double clicking into the time line above the [event view](#).

In the [playback menu](#) there are additional actions which can move the cursor to the next or previous measure ( and ), the next or previous marker ( and ), or reset the cursor to start the playback at the beginning of the file ().




6.3) Speed



Sometimes it will be useful to slow down the playback speed (or to speed it up). This can be done by setting the playback speed in the [playback menu](#). Setting the playback speed to 1 (default) will play at normal speed, while setting it to 2 will result in a two times faster playback speed. Playback speeds lower than 1 will slow down the playback.

6.4) Metronome

🔊 The metronome can be enabled or disabled in the [playback menu](#) or in the toolbar. Enabling the metronome will result in a metronome sound at each beat during the playback.

6.5) Locking the Screen


When you play a song and there must not be any delays while playing you may have to lock the screen by enabling  in the [playback menu](#). This means that the [event view](#) does not follow the cursor while playing, because the repainting of the window can cause a short delay on slower machines.



7) Recording Midi Data

MidiEditor is able to record Midi data from an [input device](#), e.g. a digital piano.

To start a recording, press the record button in the [playback menu](#) or in the toolbar. MidiEditor will start a [playback](#) (which will allow you to hear any in advance entered Midi events) and listen to the [input device](#) at the same time. Hence, played notes (and other events) which were entered using the [input device](#) can be added to the currently loaded Midi file which will add the events at the time they were played.



After a recording has been finished, click the stop button in the [playback menu](#) or in the toolbar. If any events have been recorded, a dialog will pop up which allows you to specify how to handle the recorded events.

You can ignore some event types. All events with this type will not be added to the file, all other events will be added at the time they have been played. You can specify the track and the channel of the recorded events in the dialog. Pressing "Ok" will add the events to the file.

After the events have been added, you may want to edit the events. This can include correcting wrong notes or adjusting the timing. Especially the [quantization function](#) will be useful in this context.