



Peacemaker Manual

written by

Michael von Domaros,
Johannes Ingenmey

June 19, 2021

Contents

1	Compiling Peacemaker	4
2	Running Peacemaker	4
3	Parallelization Strategy	4
4	Peacemaker Configuration Files	5
5	The Peacemaker Input File	5
5.1	Examples	5
5.2	Section [system]	7
5.3	Section [qce]	7
5.4	Section [reference]	8
5.5	Section [output]	9
6	The Peacemaker Clusterset File	9
6.1	Example	9
6.2	Details	10
7	Peacemaker Output Files	11
8	Parameter Sampling	12

1 Compiling Peacemaker

Peacemaker is a modern FORTRAN code and thus requires a modern FORTRAN compiler. We recommend a recent version of gfortran which is used for active development.

Peacemaker can be built by running

```
$ make release
```

which should produce a run time optimized binary called peacemaker. In case of errors, adjust the makefile to your compiler. We recommend the following compiler flags or your compiler's equivalents:

```
-O3 highest optimization level that guarantees standard compliance  
-fopenmp OpenMP parallelization  
-flto link-time optimization
```

A version suitable for development and debugging can be built by running

```
$ make debug
```

Note: Older versions of gfortran are subject to a bug which prevents OpenMP parallelization. If you receive the error message “Attempting to allocate already allocated variable ‘ib’ ”, compile without OpenMP support, or upgrade to a newer compiler version.

2 Running Peacemaker

Peacemaker is run by

```
$ peacemaker [input] [clusterset]
```

where [input] is the location of the input file and [clusterset] is the location of the clusterset file. The structure of both files will be explained in section 4 on the following page.

If Peacemaker was compiled with OpenMP parallelization, it can be run in parallel by

```
$ OMP_NUM_THREADS=[N] peacemaker [input] [clusterset]
```

In this case, [N] specifies the number of threads to run with.

3 Parallelization Strategy

Peacemaker parallelizes the a_{mf} , b_{xv} sampling. The workload is shared among all available threads. Thus almost perfect parallel efficiency can be expected for large sampling ranges (or a fine grid), but no speedup should be expected if a very large number of clusters or many temperatures are investigated.

4 Peacemaker Configuration Files

Both the input and the clusterset file share a common format which shall be briefly explained here. The general structure of any of those files is:

```
[section1]
    keyword1 argument1 argument2 ...# comment
    keyword2 argument1 argument2 ...
    ...
[section2]
    keyword1 argument1 argument2 ...
    keyword2 argument1 argument2 ...
    ...
...
```

Thus there are sections, which shall be embraced in brackets, keywords, arguments, and comments. Section labels are unique. Keywords within a section are unique. Arguments are optional. Comments may start anywhere and are introduced by the number sign `#`. All elements are case sensitive.

5 The Peacemaker Input File

5.1 Examples

The following input file will run a QCE "single point" calculation for a one-component system using the clusterset specified in the command line and explained in section 6 on page 9. Default options are used in most cases.

```
[qce]
    amf 0.1 # J*m^3/mol^2
    bxv 1.3
[ensemble]
    temperature 200.0 400.0 201 # K
    pressure 1.01325 # bar
    monomer_amounts 1.0 # mol
```

The following input will perform an a_{mf} , b_{xv} parameter sampling for a pure substance. Reference data are provided by an isobar file. Further details on parameter sampling are explained in section 8 on page 12.

```

[system]
  components 1
[qce]
  amf 0.0 0.5 101 # J*m^3/mol^2
  bxv 1.0 2.0 101
[ensemble]
  temperature 200.0 400.0 201 # K
  pressure 1.01325 # bar
  monomer_amounts 1.0 # mol
[reference]
  isobar isobar.dat

```

The following input will perform an a_{mf} , b_{xv} parameter optimization for a ternary mixture, following a rough sampling on a small grid. Reference data are provided by a density at 298.15 K and a temperature of phase transition.

```

[system]
  components 3
[qce]
  amf 0.0 2.0 11 # J*m^3/mol^2
  bxv 0.5 1.5 11
  grid_iterations 2
  optimizer 11
[ensemble]
  temperature 273.15 400.15 128 # K
  pressure 1.01325 # bar
  monomer_amounts 0.6 0.1 0.3 # mol
[reference]
  density 298.15 0.9248 # K; g/cm^3
  phase_transition 332.61 # K

```

While hopefully self-explaining, all sections and their associated keywords shall be explained in the following.

5.2 Section [system]

`components` N

The number of components in the system. Currently only 1 (pure) and 2 (binary) are supported. Note that although it is possible to run a pure system as binary system, where the amount of one of the species is set to zero, we strongly encourage you to run such calculations as a pure system. Results will be the same in either case, but slow convergence may arise for some temperatures if the amount of monomers of one component is sufficiently small. Optional. Default: 1

5.3 Section [qce]

`amf` A

`amf` A B N

The mean field parameter a_{mf} in units of $\text{J m}^3 \text{mol}^{-2}$. Can be specified either as a single value A, or as a range A, B, N, where A is the start, B the end, and N the number of data points (including both boundaries). For multi-component mixtures, this keyword is equivalent to `amf_mix`. Optional. Default: 0.0

`bxv` A

`bxv` A B N

The exclusion volume scaling parameter b_{xv} . Can be specified either as a single value A, or as a range A, B, N, where A is the start, B the end, and N the number of data points (including both boundaries). Optional. Default: 1.0

`amf_temp` A

`amf_temp` A B N

The linear temperature dependence parameter $a_{\text{mf,temp}}$ of the mean field. **Experimental! Do not use.** Optional. Default: 0.0

`bxv_temp` A

`bxv_temp` A B N

The linear temperature dependence parameter $b_{\text{xv,temp}}$ of the exclusion volume. **Experimental! Do not use.** Optional. Default: 0.0

`grid_iterations` A

The number of iterations for the parameter sampling if a sampling grid is specified. With each iteration, the grid center is moved to the best parameter pair and the grid size is decreased with a factor of 0.2. Optional. Default: 1

`rotor_cutoff` A

The cutoff frequency in cm^{-1} at which the RRHO-correction for low frequencies will be used. To limit their influence on the entropy, vibrational modes with a frequency below A will be treated as hindered rotations, employing a switching function to smooth the transition between harmonic oscillator and rigid rotator. If set to 0, no correction will be applied. Optional. Default: 0

`optimizer` A

Enables the Nelder–Mead algorithm for parameter optimization. A is a 4 bit num-

ber that specifies which parameters should be optimized. Each optimizable parameter is assigned a specific value:

a_{mf}	1
b_{xv}	10
$a_{\text{mf,temp}}$	100
$b_{\text{xv,temp}}$	1000

A is the sum of the values associated with the parameters that should be optimized, i.e., to optimize a_{mf} and b_{xv} it should be set to 11. **All settings except 0 and 11 should currently be considered experimental.** Optional. Default: 0

max_deviation A

The maximum relative deviation of the Gibbs energy. Used to check convergence of the QCE iteration. A QCE cycle has converged, if

$$\left| \frac{G(\text{current step}) - G(\text{last step})}{G(\text{last step})} \right| < A.$$

Optional. Default: 1.0e-9

volume_damping_factor A

The volume damping factor used to damp the initial volume guess if one of the polynomials did not converge. Shall be between 0 and 1. Damping is performed by $\gamma_V = 1 \pm A$, depending on the mode of the temperature loop. Optional. Default: 0.01

qce_iterations N

The maximum number of iterations in a QCE cycle. Optional. Default: 100

newton_iterations N

The maximum number of iterations in a Newton–Raphson cycle. Optional. Default: 500

5.4 Section [reference]

This section is optional. It enables comparison to experimental reference data. It is disabled by default. Further details on parameter sampling are given in section 8 on page 12.

density A B

density A B C

Reference density B in units of g cm^{-3} at reference temperature A in K and an optional error weight C. Optional.

isobar P

isobar P A

Path to an isobar file P and an optional error weight A. Isobar files contain two columns representing the temperature in K and volume in L. Optional.

`phase_transition A`

`phase_transition A B`

Reference temperature of phase transition A in units of K and an optional error weight B. Optional.

5.5 Section [output]

This section is optional. It enables output control. It is disabled by default.

`contributions`

`contributions <helmholtz|internal|entropy|cv>`

Enables the output of contributions of each degree of freedom to the thermodynamic functions. If no arguments are given, contribution output is enabled for all possible thermodynamic quantities. If arguments are specified, contribution output is only enabled for the selected thermodynamic quantities. Optional.

`progress`

`noprogress`

Enables or disables the progress bar. Optional. Default: enabled.

6 The Peacemaker Clusterset File

6.1 Example

Clusterset files are structured like input files. A section provides all necessary information about a cluster. The section label is used as cluster label. Cluster data may be acquired with the help of the tools provided with this distribution of Peacemaker. See the tools/README file for further information.

```

[Cluster 1]
    monomer
    composition 1
    sigma 2
    coordinates /home/user/clusters/cluster1.xyz
    frequencies /home/user/clusters/cluster1.flist
    energy 0.0
    volume 60.0
    frequency_scale 0.97

[Cluster 2]
    composition 3
    sigma 3
    coordinates /home/user/clusters/cluster2.xyz
    frequencies /home/user/clusters/cluster2.flist
    energy -20.0
    frequency_scale 0.97

...

```

6.2 Details

monomer

Sets the current cluster as monomer. Optional, but must be present once for each component.

composition N M

Composition of the cluster in number of monomers. One number for each component.

sigma N

The rotational symmetry number of the cluster.

coordinates P

Path to a coordinate file in the xyz format. Units are Å.

frequencies P

Path to a frequency file. It contains the number of frequencies in line 1, followed by a comment line, followed by one frequency per line. Units are cm^{-1} .

energy A

The adiabatic interaction energy of the cluster in units of kJ mol^{-1} (negative energies represent stable clusters).

volume A

The volume of the cluster in units of \AA^3 . Must be specified for monomers, only.

frequency_scale A

A frequency scaling factor. Optional.

anharmonicity A

The anharmonicity constant. Optional.

7 Peacemaker Output Files

Peacemaker writes results for the best a_{mf} , b_{xv} parameter pair if it could be determined or for the first a_{mf} , b_{xv} pair otherwise. In the following, the output files shall be briefly described. All output files contain the temperature in K in column 1.

volume.dat

Contains the volume and related quantities: volume V in dm^3 , exclusion volume V_{excl} in dm^3 , volumetric expansion coefficient α in K^{-1} , status code for debugging purposes.

thermo0.dat

Contains thermodynamic quantities that do not depend on any derivative: Helmholtz free energy A in kJ, Gibbs free energy G in kJ.

thermo1.dat

Contains thermodynamic quantities that depend on first derivatives: internal energy U in kJ, enthalpy H in kJ, entropy S in J/K.

thermo2.dat

Contains thermodynamic quantities that depend on second derivatives: heat capacity at constant volume c_V in J/K, heat capacity at constant pressure c_P in J/K.

xxx_contrib.dat

Contains contributions of each degree of freedom to the quantity denoted by xxx. Possible quantities are: Helmholtz free energy, internal energy, entropy, heat capacity at constant volume.

xxx_clusters.dat

Contains the contributions of each cluster to the quantity denoted by xxx divided by its absolute population (meaning these are cluster specific quantities). Possible quantities are: the partition function and its derivatives, the indistinguishability contribution, Helmholtz free energy, internal energy, Gibbs energy, enthalpy, entropy, heat capacity at constant volume and pressure.

populations.dat

Contains populations of each cluster in the order they were specified in the cluster set. Populations are monomer normalized. For example, in a binary system:

$$N'_\varnothing = \frac{(i_\varnothing + j_\varnothing) N_\varnothing}{N_{1,\text{tot}} + N_{2,\text{tot}}}. \quad (1)$$

Generally, in a multi-component system:

$$N'_\phi = \sum_c \frac{i_c \cdot N_\phi}{N_{c,\text{tot}}}. \quad (2)$$

`concentrations.dat`

Contains concentrations in mol/l of each cluster in the order they were specified in the cluster set. Concentrations are not monomer normalized.

8 Parameter Sampling

Peacemaker performs a_{mf} , b_{xv} parameter sampling on a grid, which can be specified in the [qce] section of the input file. For each pair, the quality of the resulting isobar is compared to certain experimental quantities. The following options are available for this purpose: single density, isobar, temperature of phase transition. The isobar quality is computed according to the following equation.

$$\text{error} = w_{\text{density}} \left(\frac{\rho - \rho^{\text{exp}}}{\rho^{\text{exp}}} \right)^2 + w_{\text{isobar}} \frac{1}{N} \sum_{i=1}^N \left(\frac{V_i - V_i^{\text{exp}}}{V_i^{\text{exp}}} \right)^2 + w_{\text{phase transition}} \left(\frac{T_{\text{pt}} - T_{\text{pt}}^{\text{exp}}}{T_{\text{pt}}^{\text{exp}}} \right)^2$$

Any combination of the experimental data above can be chosen. The relative importance of each quantity can be specified by the weight w .

Isobars are specified by an isobar file. This file shall contain two columns of numbers: temperatures in K in column one and volumes in dm^3 in column two. All temperatures must be within the temperature range specified in the [qce] section. There are no requirements on the order of the temperatures. Temperatures may be included multiple times to put special weight on them. If a reference temperature is not equal to the temperature specified by the temperature range in the [qce] section, linear interpolation between the two closest temperatures is performed.