

GeoNetwork Administrator's Guide

Authors: **ANDREA CARBONI, FRANÇOIS PRUNAYRE**

Revision 7 (04-Oct-2007)

Contents

I	Web interface	2
1	Basic configuration	3
1.1	System configuration	3
1.2	Localization	6
2	Import facilities	9
2.1	Batch import	9
2.1.1	Structured import	10
3	Harvesting	13
3.1	Introduction	13
3.2	Mechanism overview	13
3.3	Harvesting lifecycle	14
3.4	Multiple harvesting and hierarchies	14
3.5	General notes and issues	15
3.6	The main page	16
3.6.1	Harvesting result tips	18
3.7	Adding new nodes	19
4	Metadata ownership	30
4.1	Introduction	30
4.2	Access policy	30
4.3	Privileges	31
4.4	Ownership transfer	31

5	Thesaurus	34
5.1	Introduction	34
5.2	Thesaurus / SKOS format	34
5.3	Thesaurus administration	35
5.3.1	Creation of a new thesaurus	35
5.3.2	Import existing thesaurus	36
5.4	Editing/browsing thesaurus : add/remove/browse keywords	37
5.5	Metadata editing : adding keywords	37
5.6	Search criteria : keywords	39
II	GAST	40
6	Introduction	41
6.1	What is GAST?	41
6.2	Starting GAST	41
6.3	Operating modes	42
6.4	Tools subdivision	43
6.5	Configuration dialog	43
7	Import / export tools	45
7.1	Introduction	45
7.2	Export	45
7.3	Import	46
7.4	A note on ownership	47

Introduction

The purpose of this document is to explain how to use, configure and administer GeoNetwork using its graphical tools. These tools are subdivided into 2 main categories:

- **Web tools** : these are directly accessible from the web interface and allow the user to tune almost all aspects of GeoNetwork.
- **GAST tools** : these are special tools that cannot be executed while GeoNetwork is running or that perform special tasks better done in a separate tool.

Part I

Web interface

Chapter 1

Basic configuration

1.1 System configuration

Most of the GeoNetwork's configuration parameters can be changed using the web interface. Those parameters that cannot be changed through the web interface can be usually changed using the GAST application. To reach this web interface, you must be logged in as an Administrator. The page's link is located into the administration page (see figure 1.1. The link is surrounded with a red rectangle).

Clicking the page's link you will get the set of parameters that you can change (see figure 1.2). Here follows a detailed description of them:

Site	General site parameters.
name	The name of the GeoNetwork's installation. This name will be used to identify the node in operations like the harvesting.
organization	The organization the node belongs to. Just for informative reasons.
Server	Here you have to enter the address of your GeoNetwork's node. This address is important because it will be used to access the node.
host	The node's address or IP number. If your node is publicly accessible from the Internet, you have to use the machine's domain/address. If your node is hidden into your private network and you have a firewall or web server that redirects incoming calls to the node, you have to enter the public address of the firewall or web server. A typical configuration is to have an Apache web server on address A that is publicly accessible and redirects the requests to a Tomcat server on a private address B . In this case you have to enter A in the host parameter.

Administration	
Metadata	
New metadata	Adds a new metadata into geonetwork copying it from a template
XML Metadata Insert	Import XML formatted metadata
Batch Import	Import all XML formatted metadata from a local directory
Search for Unused	Search for unused or empty metadata
Personal info	
Change password	Allow current user to change password
Change user information	Allow current user to change user information
Administration	
User management	Add/modify/delete and show users
Group management	Add/modify/delete and show groups
Category management	Add/modify/delete and show categories
Harvesting management	Add/modify/delete/start/stop harvesting tasks
System configuration	Allows to change some system's parameters
Localization	Allows to change localized entities, like groups, categories etc...

Figure 1.1: How to reach the configuration page

port The node's port (usually 80 or 8080). If the node is hidden, you have to enter the port on the public firewall or web server.

Intranet A common need for an organization is to discriminate between internal anonymous users (users that access the node from within the organization) and external ones (users from the Internet). Node's administrators can specify different privileges for internal and external anonymous users and, in order to do so, they have to specify the parameters of the internal network.

network The internal network's address in IP form.

netmask The network's mask.

Z39.50 GeoNetwork can act as a Z39.50 server, which is an OGC communication protocol to query and retrieve metadata.

enable check this option to start the Z39.50 submodule. Please, notice that GeoNetwork must be restarted in order to make this change active.

port This is the port on which GeoNetwork will be listening for incoming Z39.50 requests. Usually, the value of 2200 is a standard one, but to have multiple GeoNetwork nodes on the same machine you have to change this value in order to avoid port conflicts between the different nodes.

Proxy In some occasions (like harvesting) GeoNetwork must be able to connect to remote sites and this may be denied if an organization uses proxy servers. In this cases, GeoNetwork must be configured to use the proxy server in order to route outgoing requests.

System configuration

Site

Name

Organization

Server

Host

Port

Intranet

Network

Netmask

Z39.50 Server

Enable ☒

Port

Proxy

Use ☒

Host

Port

Feedback

EMail

SMTP Host

SMTP Port

Figure 1.2: The configuration options

host The proxy's name or address to use (usually an IP address).

port The proxy's port to use.

Feedback GeoNetwork can provide some feedback to the administrator if some events happen, for example a metadata is downloaded or some feedback is provided using the online form. You have to configure GeoNetwork with proper parameters to send an email.

email This is the email address that will be used to send feedback to the administrator.

SMTP host Organization's mail server to use when sending emails

SMTP port Mail server's SMTP port (usually 25).

At the bottom of the page there are some buttons with the following purpose:

- | | |
|----------------|--|
| Back | Simply returns to the main administration page. |
| Save | Saves the current options. If some options are invalid, the system will show a dialog with the wrong parameter and will focus its textfield on the page. Once the configuration is saved a success dialog will be shown. |
| Refresh | This button simply refreshes the displayed options taking the new values from the server. This can be usefull if some options get changed dynamically (for example by another user). |

Public host and port usage

Up to now, the server's host and port are used in these cases:

- During an editing session, when adding data links to a metadata. The host and port will be used to build download links to store inside the metadata.
- During CSW requests. The GetCapabilities operation returns an XML document with HTTP links to the CSW services. These links are dynamically built using the host and port values.

1.2 Localization

The GeoNetwork's user interface can be easily localized into several languages just adding a few XML files. Anyway, beside static labels on the web page there are some dinamic entities that can be created and changed for which a simple XML file is not enough. These entities are stored inside the database and their localization can be performed using a specialized web form which can be reached from the administration page (see figure 1.3).

This form allows you to localize all entities whose structure is similar: a short non localized name and several localized labels, one for each supported language. Up to now, you can localize the following entities: *groups*, *categories*, *operations* and *regions*. The form is shown in figure 1.4 and is subdivided into a left and a right panel.

The left panel allows you to choose which entity you want to edit. On the top, a dropdown let you choose which entity type to edit. All entities of a choosen type are shown in a list on the bottom part of the panel (actually, the short names are listed).

The right panel allows a translator to read the label in a source language and translate it into a target language. The user can change both the source and the target languages using the provided dropdown

Administration	
Metadata	
New metadata	Adds a new metadata into geonetwork copying it from a template
XML Metadata Insert	Import XML formatted metadata
Batch Import	Import all XML formatted metadata from a local directory
Search for Unused	Search for unused or empty metadata
Personal info	
Change password	Allow current user to change password
Change user information	Allow current user to change user information
Administration	
User management	Add/modify/delete and show users
Group management	Add/modify/delete and show groups
Category management	Add/modify/delete and show categories
Harvesting management	Add/modify/delete/start/stop harvesting tasks
System configuration	Allows to change some system's parameters
Localization	Allows to change localized entities, like groups, categories etc...

Figure 1.3: How to reach the localization page

controls. The label in the source language is read only while the one in the target language is the one that needs to be localized. When the user changes the target label, the textarea becomes yellow to indicate a change. When the label becomes equal to the initial one again, the textarea becomes white.

On the bottom of the form there are some buttons:

- Back** Simply returns to the administration page.
- Save** Saves the current target label to the server and advances to the next one. The normal workflow is to select first both a source and a target language. Then, the user goes through all entities localizing on at time. It is important to notice that if the user changes a label and chooses another target language, the label change is lost so it is better to localize labels in one language at time.
- Refresh** Reloads all entities of the selected type and any previous cache of other loaded types is invalidated. This button is useful when the number of entities changes (added or removed by other users).

Localization


Entity

Source language

Case studies, best practices

Target language

Etude de cas, meilleurs pratiques



Entity	Source language	Target language
maps		
datasets		
interactiveResources		
applications		
caseStudies	Case studies, best practices	Etude de cas, meilleurs pratiques
proceedings		
photo		
audioVideo		
directories		
otherResources		

Figure 1.4: The localization form

Chapter 2

Import facilities

2.1 Batch import

The batch import facility allows you to import a set of metadata into the system all at once. In order to use this facility, you have to be logged in as an administrator. After the login step, go to the administration page and select the batch import's link (see figure 2.1. The link is surrounded with a red rectangle).

Clicking the link, you will reach the batch import's page as illustrated in figure 2.2. You have to specify a set of parameters to make the import working. They are:

- Directory** This is the full path on the server's file system of the directory to scan. GeoNetwork will look for and try to import all XML files present into this directory. It is important to notice that this is the directory on the *server* machine and *not* on the client of the user that is doing the import. All metadata files present into the import directory *must* have the same schema format.
- Schema** GeoNetwork supports only some metadata formats so you have to specify the schema of the metadata you want to import. If a metadata does not belong to the selected schema, the entire operation will be aborted.
- Validate** This is a simple validation step that you can choose to perform. The metadata is validated against its schema.
- Group** You have to select a group to associate to the imported metadata. Usually the group is the creator of the metadata set.
- Category** You can specify one category to associate to your metadata in order to simplify the search.

Administration	
Metadata	
New metadata	Adds a new metadata into geonetwork copying it from a template
XML Metadata Insert	Import XML formatted metadata
Batch Import	Import all XML formatted metadata from a local directory
Search for Unused	Search for unused or empty metadata
Personal info	
Change password	Allow current user to change password
Change user information	Allow current user to change user information
Administration	
User management	Add/modify/delete and show users
Group management	Add/modify/delete and show groups
Category management	Add/modify/delete and show categories
Harvesting management	Add/modify/delete/start/stop harvesting tasks
System configuration	Allows to change some system's parameters
Localization	Allows to change localized entities, like groups, categories etc...

Figure 2.1: How to reach the batch import page

Stylesheet This is a powerfull option because allows you to specify a stylesheet for an XSL transformation. The drop down control is filled with files taken from the `web/xsl/conversion/import` folder : all XSL files you put there will be made available. This is a dymanic process so you don't have to restart GeoNetwork. The purpose of this option is to allow the conversion of a metadata into a suitable format that is supported by GeoNetwork. Therefore, it is important that the result of the transformation matches the schema format selected above.

Below the page, there are the following buttons:

Back Goes back to the administration form.

Upload Starts the import process. When the process ends, the total count of imported metadata will be shown. Please notice that the import is transactional: the metadata set will be fully imported or fully discarded (there are no partial imports). Files that starts with '.' or that do not end with '.xml' are ignored.

2.1.1 Structured import

An hidden feature of the batch import is the possibility to specify some import parameters in more detail. This feature is triggered when the specified folder contains the **import-config.xml** file. When this happen, this file is read and the standard import switches to the structured one.

The import-config.xml file has a **config** root element with the following children:

Import all XML formatted metadata from a local directory

Directory

Schema

Validate ☐

Group

Category

StyleSheet

Figure 2.2: The batch import options

- **categoryMapping** [1] : this element specifies the mapping of directories to categories.
 - **mapping** [0..n] : This element can appear 0 or more times and maps one directory name to a category name. It must have a **dir** attribute that indicates the directory and a **to** attribute that indicates the category name.
 - **default** [1] : This element specifies a default mapping of categories for all directories that do not match the other mapping elements. It must have only the **to** attribute.
- **schemaMapping** [1] : this element specifies the mapping of directories to metadata schemas.
 - **mapping** [0..n] : This element can appear 0 or more times and maps one directory to the schema name that must be used when importing. The provided schema must match the one used by the metadata contained into the specified directory, which must all have the same schema. It must have a **dir** attribute that indicates the directory and a **to** attribute that indicates the schema name.
 - **default** [1] : default behaviour to use when all other mapping elements do not match. It must have only the **to** attribute.

Here is an example of the **import-config.xml** file:

```
<config>
  <categoryMapping>
    <mapping dir="1" to="maps" />
    <mapping dir="3" to="datasets" />
    <mapping dir="6" to="interactiveResources" />
    <mapping dir="30" to="photo" />
    <default to="maps" />
  </categoryMapping>
  <schemaMapping>
    <mapping dir="3" to="fgdc-std" />
    <default to="dublin-core" />
  </schemaMapping>
</config>
```

The import procedure starts by scanning the provided directory. This can contain, beside the **import-config.xml** file, only subdirectories which name will be ignored but used only as a container. Inside each directory, there is another level made only by directories that represent a metadata grouping for categories. Each directory name will be used as the **dir** attribute in the mapping scheme previously described.

Chapter 3

Harvesting

3.1 Introduction

Since the beginning of the project, there has been the need to share metadata among several GeoNetwork nodes. Usually, each node takes care of a region of interest so it is important to be able to perform a search over all these nodes at the same time. This is called distributed search and exploits the Internet connectivity. In our cases, this distributed search can be heavy to perform if there are many maps with associated thumbnails. Furthermore, GeoNetwork is usually employed in countries (like Africa, Brazil) where the connectivity is bad, making the use of distributed search not feasible.

The **harvesting** is the process of collecting remote metadata and storing them locally for a faster access. This is a periodic process to do, for example, once a week. Harvesting is not a simple import: local and remote metadata are kept aligned. Using some *magic*, GeoNetwork is capable of discovering metadata that have been added, removed or updated.

GeoNetwork is able to harvest from the following sources (for more details see below):

- Another GeoNetwork node (version 2.1 or above).
- A web DAV server.
- A CSW 2.0.1 server.
- An old GeoNetwork 2.0 node.
- An OAI-PMH server.

3.2 Mechanism overview

The harvesting mechanism is based on the concept of *universally unique identifier* (uuid). This is a special id because it is not only unique locally to the node that generated it but it is unique across all

the world. It is a combination of the network interface's MAC address, the current date/time and a random number. Every time you create a new metadata in GeoNetwork, a new uuid is generated and assigned to it.

Another important concept behind the harvesting is the *last change date*. Every time you change a metadata, its last change date is updated. Just storing this parameter and comparing it with a new one allows any system to find out if the metadata has been modified since last update.

These two concepts allow GeoNetwork to fetch a remote metadata, check if it has been updated and remove it locally if it has been removed remotely. Furthermore, thanks to uuids, a hierarchy of harvesting nodes can be built where B harvests from C and A harvests from B. Even loops can be created because harvested metadata cannot be modified.

3.3 Harvesting lifecycle

When a harvesting node is set, there is no harvested metadata. During the first run, all remote matching metadata are retrieved and stored locally. After the first run, only changed metadata are retrieved. Harvested metadata are not editable for the following reasons:

- The harvesting is periodic so any local change to harvested metadata will be lost during the next run.
- The change date is used to keep track of changes so if it gets changed outside the originator site, the harvesting mechanism is compromised.

Beside the metadata itself, this implies that users cannot change all other metadata properties (like categories, privileges etc...).

The harvesting process goes on until one of the following situations arises:

- An administrator stops (deactivates) the node.
- An exception arises. In this case the node is automatically stopped.

When a harvesting node is removed, all harvest metadata are removed too.

3.4 Multiple harvesting and hierarchies

Catalogues that provide uuids for metadata (for example GeoNetwork and a CSW server) can be harvested several times without having to take care about metadata overlap. This allows the possibility to perform a thematic search and a metadata belonging to multiple searches is harvested only once and not duplicated.

This mechanism allows the GeoNetwork harvesting type to be combined with other GeoNetwork nodes to perform hierarchical harvesting. This way a metadata can be harvested from several nodes. For example, consider this scenario:

- Node (A) has created metadata (a)
- Node (B) harvests (a) from (A)
- Node (C) harvests (a) from (B)
- Node (D) harvests from both (A), (B) and (C)

In this scenario, Node (D) will get the same metadata (a) from all 3 nodes (A), (B), (C). The metadata will flow to (D) following 3 different paths but thanks to its uuid only one copy will be stored. When (a) will be changed in (A), a new version will flow to (D) but, thanks to the change date, the copy in (D) will be updated with the most recent version.

3.5 General notes and issues

General

- The harvesting engine does not store harvesting results. This implies that if the server is restarted the last results are lost.
- Changes to the harvesting parameters (for example privileges and categories) are taken into account in the next harvesting run.

GeoNetwork harvesting type

- During harvesting, site icons are harvested and local copies updated. Icons are propagated to new nodes as soon as these nodes harvest from this one.
- The metadata uuid is taken from the info.xml file of the MEF bundle. Any uuid stored inside the metadata will be overwritten with this one.

WebDAV harvesting type

- The same metadata could be harvested several times by different harvesting nodes. Anyway, this is not a good practice because every copy of the metadata will have a different uuid and the system will fill with different copies of the same metadata.

Administration	
Metadata	
New metadata	Adds a new metadata into geonetwork copying it from a template
XML Metadata Insert	Import XML formatted metadata
Batch Import	Import all XML formatted metadata from a local directory
Search for Unused	Search for unused or empty metadata
Personal info	
Change password	Allow current user to change password
Change user information	Allow current user to change user information
Administration	
User management	Add/modify/delete and show users
Group management	Add/modify/delete and show groups
Category management	Add/modify/delete and show categories
Harvesting management	Add/modify/delete/start/stop harvesting tasks
System configuration	Allows to change some system's parameters
Localization	Allows to change localized entities, like groups, categories etc...

Figure 3.1: How to reach the harvesting main page

CSW harvesting type

- If the **dct:modified** element is missing from the **GetRecords** response the metadata will be always harvested.
- Any exception during **getRecordById** operation is discarded and the metadata skipped.

OAI-PMH harvesting type







- The **id** of the remote server **must** be a uuid. If not, metadata can be harvested but during hierarchical propagation id clashes could corrupt harvested metadata.
- During harvesting, GeoNetwork will try to autodetect the schema of each metadata. If the schema is not supported the metadata is skipped.

3.6 The main page

To reach the harvesting main page you have to be logged in as an administrator. From the administration page, click the link shown in figure 3.1 with a red rectangle.

Figure 3.2 shows the harvesting main page. The page shows a list of harvesting nodes that have been created so far. On the bottom side there is a set of buttons to manage these nodes. The meaning of each column is as follows:

HARVESTING MANAGEMENT

Select	Name	Type	Status	Errors	Every	Last run	Operation
<input type="checkbox"/>	Dav test	Web DAV			0:5:5		Edit
<input type="checkbox"/>	FAO site	GeoNetwork			0:1:30		Edit
<input type="checkbox"/>	CSW	CSW/2.0			0:1:30		Edit

Activate

Deactivate

Run

Remove

Back

Add

Refresh

Figure 3.2: The harvesting main page

- Select** This is just a checkbox to select one or more nodes. The selected nodes will be affected by the first row of buttons (start, stop, run, remove). For example, if you select 3 nodes and press the **Remove** button, these 3 nodes will be removed.
- Name** This is the node's name provided by the administrator.
- Type** The node's harvesting type choosed when the node was created (geonetwork, web folder etc...).
- Status** This is an icon that reflects the node's current status. See figure 3.3 for all different icons and status description.
- Errors** This column reflects the status of the last harvesting run, which could have succeeded or not. The result is reflected on this icon and a tooltip will show detailed information. See figure 3.4 for all different icons.
- Every** Time (in days, hours, minutes) between two consecutive harvesting from this node.
- Last run** The date, in ISO 8601 format, of the most recent harvesting run.
- Operation** A list of buttons for all possible operations on a node. At least, an **Edit** button is present. Pressing this button you will reach the same page used to create the node. From this page you can change the desired parameters.

The bottom side of the page contains two rows of buttons. The first row contains buttons that can operate on a set of nodes. You can select the nodes using the checkbox on the first column and then press the proper button. When the button finishes its action, the checkboxes are cleared. The second row contains general purpose buttons. Here is the meaning of each button:

- Activate** When a new harvesting node is created, it's status is *inactive*. Use this button to make it *active* and thus to start harvesting from the remote node.




Icon	Status	Description
	Inactive	The harvesting from this node is stopped.
	Active	The harvesting engine is waiting for the timeout specified for this node. When the timeout is reached, the harvesting starts.
	Running	The harvesting engine is currently running, fetching metadata from remote nodes. When the process will be finished, the status will be switched to active.

Figure 3.3: Possible status icons



Icon	Description
	The harvesting was ok, no errors were found. In this case, a tooltip will show some harvesting results (like the number of harvested metadata etc...). See section 3.6.1.
	The harvesting was aborted due to an unexpected condition. In this case, a tooltip will show some information about the error.

Figure 3.4: Possible error icons

- Deactivate** Stops harvesting from a node. Please notice that this does not mean that a currently running harvesting will be stopped but it means that this node will be ignored during future harvestings.
- Run** This button simply tells the harvesting engine to start harvesting immediately. This is usefull for testing during the harvesting setup.
- Remove** Remove all currently selected nodes. A dialog will ask the user to confirm the action.
- Back** Simply returns to the main administration page.
- Add** This button allows to create new harvesting nodes. See section 3.7 for more information.
- Refresh** Refreshes the current list of nodes quering the server. This can be usefull to see if the harvesting list has been altered by someone else or if any harvesting process started.

3.6.1 Harvesting result tips

If the harvesting succeeds, a tooltip will show detailed information about the harvesting process. This way you can check if the harvester worked as expected or if there is something to fix to the harvesting parameters or somewhere else. The result tip is like a table, where each row refers to

- Total** This is the total number of metadata found remotely. Metadata with the same id are considered as one.

Result vs harvesting type	Geonet	Web DAV	CSW	OAI-PMH
Total	x	x	x	x
Added	x	x	x	x
Removed	x	x	x	x
Updated	x	x	x	x
Unchanged	x	x	x	x
Unknown schema	x	x	x	x
Unretrievable	x	x	x	x
Bad Format		x		x
Does Not Validate		x		x

Figure 3.5: Result information supported by harvesting types.

- Added** Number of metadata added to the system because they were not present locally.
- Removed** Number of metadata that have been removed locally because they are not present in the remote server anymore.
- Updated** Number of metadata that are present locally but that needed to be updated because their last change date was different from the remote one.
- Unchanged** Local metadata left unchanged. Their remote last change date did not change.
- Unknown schema** Number of skipped metadata because their format was not recognized by GeoNetwork.
- Unretrievable** Number of metadata that were ready to be retrieved from the remote server but for some reason there was an exception during the data transfer process.
- Bad Format** Number of skipped metadata because they did not have a valid XML representation.
- Does not validate** Number of metadata which did not validate against their schema. These metadata were harvestable with success but skipped due to the validation process. Usually, there is an option to force validation: if you want to harvest these metadata anyway, simply turn it off.

3.7 Adding new nodes

The **Add** button in the main page allows you to add new harvesting nodes. After pressing it, you will reach the page shown in figure 3.6. When creating a new node, you have to choose the harvesting protocol implemented by the remote server. The supported protocols are:



Harvesting management

Type Geonetwork remote node ▼

Back Add

Figure 3.6: Adding a new harvesting node

Geonetwork This is the standard and most powerfull harvesting protocol used in GeoNetwork. It is able to log in into the remote node, to perform a standard search using the common queryable fields and to import all matching metadata. Furthermore, the protocol will try to keep both remote privileges and categories of the harvested metadata if they exist locally. Please notice that since GeoNetwork 2.1 the harvesting protocol has been improved. This means that it is not possible to use this protocol to harvest from version 2.0 or below.

Web DAV This harvesting type uses the web DAV (Distributed Authoring and Versioning) protocol to harvest metadata from a DAV server. It can be useful to users that want to publish their metadata through a web server that offers a DAV interface. The protocol allows to retrieve the contents of a web page (a list of files) with their change date.

CSW CSW stands for *Catalogue Services for the Web* and it is a search interface for catalogues developed by the Open Geospatial Consortium. GeoNetwork is compatible with version 2.0.1 of such protocol.

Old geonetwork GeoNetwork 2.1 introduced a new powerfull harvesting engine which is not compatible with the old one present in GeoNetwork 2.0. Old 2.0 servers can still harvest from 2.1 servers but a 2.1 server needs this harvesting type to harvest from old 2.0 servers. This harvesting type is deprecated and only kept until GeoNetwork 2.1 will be widely spread.

OAI-PMH The acronym stands for *Open Archive Initiative, Protocol for Metadata Harvesting*. It is a good harvesting protol widely used. GeoNetwork is compatible with version 2.0 of the protocol.

The drop down list shows all available protocols. Pressing the **Add** button you will reach an edit page whose content depends on the choosed protocol. The **Back** button will go back to the main page.

Adding a GeoNetwork node

This type of harvesting allows you to connect to a GeoNetwork node, perform a simple search as in the main page and retrieve all matched metadata. The search is usefull because it allows you to focus

only on metadata of interest. Once you add a node of this type, you will get a page like the one shown in figure 3.7. The meaning of the options is the following:

Site Here you put information about the GeoNetwork's node you want to harvest from (host, port and servlet). If you want to search protected metadata you have to specify an account. The **name** parameter is just a short description that will be shown in the main page beside each node.

Search In this section you can specify search parameters: they are the same present in the main page. Before doing that, it is important to remember that the GeoNetwork's harvesting can be hierarchical so a remote node can contain both its metadata and metadata harvested from other nodes and sources. At the beginning, the **Source** drop down is empty and you have to use the **Retrieve sources** button to fill it. The purpose of this button is to query GeoNetwork about all sources which it is currently harvesting from. Once you get the drop down filled, you can choose a source name to constrain the search to that source only. Leaving the drop down blank, the search will spread over all metadata (harvested and not). You can add several search criteria for each site through the **Add** button: several searches will be performed and results merged. Each search box can be removed pressing the small button on the left of the site's name. If no search criteria is added, a global unconstrained search will be performed.

Options This is just a container for general options.

Every This is the harvesting period. The smallest value is 1 minute while the greatest value is 100 days.

One run only If this option is checked, the harvesting will do only one run after which it will become inactive.

Privileges Here you decide how to map remote group's privileges. You can assign a copy policy to each group. The **Intranet** group is not considered because it does not make sense to copy its privileges. The **All** group has different policies from all the others:

- **Copy** : Privileges are copied.
- **Copy to intranet** : Privileges are copied but to the Intranet group. This way public metadata can be made protected.
- **Don't copy** : Privileges are not copied and harvested metadata will not be publicly visible.

For all other groups the policies are these:

HARVESTING MANAGEMENT

SITE

Name
 Host
 Port
 Servlet
 Use account ☒
 Username
 Password

SEARCH CRITERIA

☒ **Criteria**
 Free text
 Title
 Abstract
 Keywords
 Digital ☒
 Hardcopy ☐
 Source

OPTIONS

Every : : (days : hours : minutes)
 One run only ☐

PRIVILEGES

Remote group
all
sample

Copy policy

CATEGORIES

Figure 3.7: Adding a GeoNetwork node

- **Copy** : Privileges are copied only if there is a local group with the same (not localized) name as the remote group.
- **Create and copy** : Privileges are copied. If there is no local group with the same name as the remote group then it is created.
- **Don't copy** : Privileges are not copied.

Categories This section allows you to specify some local categories to assign to harvested metadata. You could create a new category for the harvesting node and assign that category to harvested metadata for a quick search using that category.

On the bottom side of the page there are some buttons:

Back Simply return to the main harvesting page.

Save Saves the current node information and returns to the main harvesting page. When creating a new node, the node will be actually created only when you press this button.

Adding a Web DAV node

In this type of harvesting, metadata are retrieved from a remote web page. The available options are shown in figure 3.8 and have the following meaning:

Site Here are the connection information. The available options are:

Name This is a short description of the node. It will be shown in the harvesting main page.

URL The remote URL from which metadata will be harvested. Each file found that ends with **.xml** will indicate a metadata and will be retrieved, converted into xml and imported.

Icon Just an icon to assign to harvested metadata. The icon will be used when showing search results.

Use account Account credentials for a basic HTTP authentication toward the remote URL.

Options General harvesting options:

Every This is the harvesting period. The smallest value is 1 minute while the greatest value is 100 days.

HARVESTING MANAGEMENT

SITE

Name

URL

Icon **REMOTE**

Use account ☒

Username

Password

OPTIONS

Every : : (days : hours : minutes)

One run only ☐

Validate ☐

Recurse ☐

PRIVILEGES

Groups

Group View Interactive map Featured

All ☒ ☐ ☐ Remove

CATEGORIES

Figure 3.8: Adding a web DAV node

One run only If this option is checked, the harvesting will do only one run after which it will become inactive.

Validate If checked, the metadata will be validate during import. If the validation does not pass, the metadata will be skipped.

Recurse When the harvesting engine will find folders, it will recursively descend into them.

Privileges Here it is possible to assign privileges to imported metadata. The **Groups** area lists all available groups in GeoNetwork. Once one (or more) group has been selected, it can be added through the **Add** button (each group can be added only once). For each added group, a row of privileges is created at the bottom of the list to allow privilege selection. To remove a row simply press the associated **Remove** button on its right.

Categories Here you can assign local categories to harvested metadata.

At the bottom of the page there are the following buttons:

Back Go back to the main harvesting page. The harvesting is not added.

Save Saves node's data creating a new harvesting node. Then it will go back to the main harvesting page.

Adding a CSW node

This type of harvesting is capable of connecting to a remote CSW server and retrieving all matching metadata. Please, note that in order to be harvested metadata must have one of the schema format handled by GeoNetwork. Figure 3.9 shows the options available, whose meaning is the following:

Site Here you have to specify the connection parameters which are similar to the web DAV harvesting. In this case the URL points to the capabilities document of the CSW server. This document is used to discover the location of the services to call to query and retrieve metadata.


Search Using the **Add** button, you can add several search criteria. You can query only the fields recognized by the CSW protocol.

Options General harvesting options:

Every This is the harvesting period. The smallest value is 1 minute while the greatest value is 100 days.

HARVESTING MANAGEMENT

SITE

Name
Capabilities URL
Icon 
Use account ☒
Username
Password

SEARCH CRITERIA

☒ **Search criteria**
Free text
Title
Abstract
Subject

OPTIONS

Every : : (days : hours : minutes)
One run only ☐

PRIVILEGES

Groups

Group	View	Interactive map	Featured	
All	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="Remove"/>
Sample group	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="button" value="Remove"/>

CATEGORIES

Figure 3.9: Adding a Catalogue Services for the Web harvesting node

One run only If this option is checked, the harvesting will do only one run after which it will become inactive.

Privileges Please, see web DAV harvesting.

Catagories Please, see web DAV harvesting.

At the bottom of the page there are the following buttons:

Back Go back to the main harvesting page. The harvesting is not added.



Save Saves node's data creating a new harvesting node. Then it will go back to the main harvesting page.

Adding an OAI-PMH node

An OAI-PMH server implements a harvesting protocol that GeoNetwork, acting as a client, can use to harvest metadata. If you are requesting the **oai_dc** output format, GeoNetwork will convert it into its dublin core format. Other formats can be harvested only if GeoNetwork supports them and is able to autodetect the schema from the metadata. Figure 3.10 shows all available options, which are:

Site All options are the same as web DAV harvesting. The only difference is that the **URL** parameter here points to an OAI-PMH server. This is the entry point that GeoNetwork will use to issue all PMH commands.

Search This part allows you to restrict the harvesting to specific metadata subsets. You can specify several searches: GeoNetwork will execute them sequentially and results will be merged to avoid the harvesting of the same metadata. Several searches allow you to specify different search criteria. In each search, you can specify the following parameters:

From You can provide a start date here. All metadata whose last change date is equal to or greater than this date will be harvested. You cannot simply edit this field but you have to use the  icon to popup a calendar and choose the date. This field is optional so if you don't provide it the start date constraint is dropped. Use the  icon to clear the field.

Until Works exactly as the **from** parameter but adds an end constraint to the last change date. The until date is included in the date range, the check is: less than or equal to.

HARVESTING MANAGEMENT

SITE

Name

Mandei

URL

http://www.mandei.org/oaipmh

Icon

default.gif

REMOTE

Use account

☒

Username

guest

Password

SEARCH CRITERIA

Criteria

From

2007-09-01

Until

Set

Maps & graphics

Prefix

oai_dc

Add

Retrieve info

OPTIONS

Every

1

:

2

:

3

(days : hours : minutes)

One run only

☐

Validate

☐

PRIVILEGES

Groups

Intranet

All

Sample group

test

Add

Group	View	Interactive map	Featured	
Sample group	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	Remove
All	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	Remove

CATEGORIES

Maps & graphics

Datasets

Interactive resources

Applications

Case studies, best practices

Conference proceedings

Photo


Audio/Video

Back

Save

Figure 3.10: Adding an OAI-PMH harvesting node

- Set** An OAI-PMH server classifies its metadata into hierarchical sets. You can request to return metadata that belong to only one set (and its subsets). This narrows the search result. Initially the drop down shows only a blank option that indicate *no set*. After specifying the connection URL, you can press the **Retrieve Info** button, whose purpose is to connect to the remote node, retrieve all supported sets and prefixes and fill the search drop downs. After you have pressed this button, you can select a remote set from the drop down.
- Prefix** Here prefix means metadata format. The **oai_dc** prefix is mandatory for any OAI-PMH compliant server, so this entry is always present into the prefix drop down. To have this drop down filled with all prefixes supported by the remote server, you have to enter a valid URL and press the **Retrieve Info** button.

You can use the **Add** button to add one more search to the list. A search can be removed clicking the  icon on its left.

Options Most options are common to web DAV harvesting. The **validate** option, when checked, will validate each harvested metadata against GeoNetwork's schemas. Only valid metadata will be harvested. Invalid one will be skipped.

Privileges Please, see web DAV harvesting.

Categories Please, see web DAV harvesting.

At the bottom of the page there are the following buttons:

- Back** Go back to the main harvesting page. The harvesting is not added.
- Save** Saves node's data creating a new harvesting node. Then it will go back to the main harvesting page.

Please note that when you edit a previously created node, both the *set* and *prefix* drop down lists will be empty. They will contain only the previously selected entries, plus the default ones if they were not selected. Furthermore, the set name will not be localized but the internal code string will be displayed. You have to press the **retrieve info** button again to connect to the remote server and retrieve the localized name and all set and prefix information.

Chapter 4

Metadata ownership

4.1 Introduction

Starting from release 2.1.0, GeoNetwork has a new metadata access policy. The old **edit** and **admin** privileges have been removed and the concept of **reviewer** has been introduced. The purpose of this new profile is to control when a metadata can be published outside or not. In previous releases, all users belonging to a group with edit privileges could edit the same metadata. Now, a metadata is only visible to its creator, to a reviewer which has access to the group owner and to an administrator.

4.2 Access policy

Def A **public metadata** is a metadata that has the **view** privilege for the group named **all**.

Visualization

An **administrator** can view any metadata.

A **reviewer** can view a metadata if :

- The group owner is one of the groups assigned to the reviewer.
- He is the metadata owner.

A **user administrator** or an **editor** can view:

- All metadata that have the **view** privilege in one of the groups visible to them.
- All metadata created by themselves.

A **registered user** can view:

- All metadata that have the **view** privilege in one of the groups visible to them.

Public metadata can be viewed by any user (logged in or not).

Editing

An **administrator** can edit any metadata.

A **reviewer** can edit a metadata if :

- The group owner is one of the groups assigned to the reviewer.
- He is the metadata owner.

A **user administrator** or **an editor** can edit only metadata created by themselves.

4.3 Privileges

The privileges administration page is accessible only by:

- All administrators
- All reviewers that have access to the metadata's group owner.
- The owner of the metadata

Regarding privileges for the **all** and **intranet** groups, only administrators and reviewers can edit them.

4.4 Ownership transfer

A typical need that arises when a user is dismissed is to transfer all their metadata to another user into another group. To fill this need, the transfer ownership functionality has been introduced. This is located in the administration page (see figure 4.1) and once selected, leads to the page shown in figure 4.2.

Initially, the page shows only a drop down for a **Source editor**. The drop down is filled with all GeoNetwork's users which are editors and own some metadata. Selecting an editor means selecting all metadata that belong to that editor. An empty drop down means that there are no editors with metadata associated and hence no transfer is possible.

ADMINISTRATION	
Metadata	
New metadata	Adds a new metadata into geonetwork copying it from a template
XML Metadata Insert	Import XML formatted metadata
Batch Import	Import all XML formatted metadata from a local directory
Search for Unused	Search for unused or empty metadata
Transfer ownership	Transfer metadata ownership to another user
Manage thesauri	Add/modify/delete and show thesauri
Personal info	
Change password	Allow current user to change password
Change user information	Allow current user to change user information
Administration	
User management	Add/modify/delete and show users
Group management	Add/modify/delete and show groups
Category management	Add/modify/delete and show categories
Harvesting management	Add/modify/delete/start/stop harvesting tasks
System configuration	Allows to change some system's parameters
Localization	Allows to change localized entities, like groups, categories etc...

Figure 4.1: How to reach the transfer ownership page.

TRANSFER OWNERSHIP			
Source editor	Andrew Athony ▼		
Source group	Target group	Target editor	Operation
Sample group	Sample group ▼	Bob Brady ▼	Transfer

Figure 4.2: The transfer ownership page.

Note The drop down will be filled with all editors visible to you. If you are not an administrator, you will view only a subset of all editors.

Once a source editor has been selected, a set of rows is displayed. Each row refers to an editor's group for which there are privileges. The meaning of each column is the following:

Source group This is a group that has privileges in the metadata that belong to the source editor. Put in another way, if one of the editor's metadata has privileges for one group, that group is listed here.

Target group This is the destination group of the transferring process. All privileges relative to the source group are transferred to the target group. The target group drop down is filled with all groups visible to the logged user (typically an administrator or a user administrator). By default, the source group is selected in the target drop down. Privileges to groups **All** and **Intranet** are not transferrable.

Target editor Once a target group is selected, this drop down is filled with all editors that belong to that target group.

Operation Actually only the **Transfer** operation is possible.

By selecting the **Transfer** operation, if the source group is different than the target group, the system performs the ownership transfer, shows a brief summary and removes the current row because now there are no privileges to transfer anymore.

Chapter 5

Thesaurus

5.1 Introduction

Thesaurus support in GeoNetwork allows :

- metadata editing : controled vocabulary on the metadata editing interface for ISO and Dublin Core
- administration interface allows import/export/creation/browse thesaurus
- search interface : a list of keyword is proposed for the keyword criteria

On a node, thesaurus types could be defined as:

- external: When a thesaurus is imported, it is flagged to "external" which means that users are not allowed to edit the thesaurus. This thesaurus is managed by an external organisation.
- local: When a thesaurus is created, it is flagged to "local" which means that users are allowed to edit the thesaurus.

5.2 Thesaurus / SKOS format

The Simple Knowledge Organisation Systems (SKOS) <http://www.w3.org/2004/02/skos/> is an area of work developing specifications and standards to support the use of knowledge organisation systems (KOS) such as thesauri, classification schemes. This format is used by GeoNetwork to store thesaurus information.

A concept is defined by an identifier, a preferred label, a definition and links with other concepts. Labels and definitions could be stored in multiple languages (using the xml:lang attributes). Three type of links between concepts have been defined in the SKOS format:

- related terms
- broader terms
- narrower terms

For example, a concept "ABLETTE" could be defined as follow with a label in french and english, linked to broader concept.:

```
<skos:Concept rdf:about="http://www.oieau.org/concept#c4fc54576dc00227b82a709287ac3681">
<skos:prefLabel xml:lang="fr">ABLETTE</skos:prefLabel>
<skos:prefLabel xml:lang="en">BLEAK</skos:prefLabel>
<skos:broader rdf:resource="http://www.oieau.org/concept#9f25ece36d04776e09492c66627cccb9"/>
</skos:Concept>
```

GeoNetwork support multilingual thesaurus (e.g. Agrovoc). Search and edition are made based on current user interface language (i.e. if the interface is in english, when editing metadata, GeoNetwork will only search for concept in english).

5.3 Thesaurus administration

To reach the thesaurus administration page you have to be logged in as an administrator. From the administration page, click the link "Manage thesaurii". Figure 5.3 shows the list of thesaurus available in the GeoNetwork node. The page shows a list of thesaurus that have been created or imported. The upper part of the page allows user to edit/add/modify/consult thesaurus. The lower part allows upload of thesaurus in SKOS format.

5.3.1 Creation of a new thesaurus

To create a new thesaurus, click the "+" sign in the category you want your thesaurus to be in. Once created, the thesaurus could be updated through the edit interface. The meaning of each column is as follows:

Type	The type allows to classify thesaurus according to its type. First, is defined the type of the thesaurus following ISO category list, then the type indicates if the thesaurus is a local one or an external one.
Name	This is the thesaurus's name provided by the administrator on creation or filename on upload. When creating a thesaurus, the name of the thesaurus will be the filename of the thesaurus.



Figure 5.1: Administration interface for thesaurus




Figure 5.2: Administration interface for thesaurus

For each thesaurus the following buttons are available:

Download Link to the rdf file.

Delete Remove thesaurus from the current node.

View If type is external, the view button allows to search and view concepts.

Edit If type is local, the edit button allows to search, add, remove and view concepts.

5.3.2 Import existing thesaurus

GeoNetwork allows thesaurus import in SKOS format. Once uploaded, an external thesaurus could not be updated. Select the category, browse for the thesaurus file and click upload. The file is located in `/web/xml/codelist/external/thesauri/category/`.

At the bottom of the page there are the following buttons:

Back Go back to the main administration page.



Figure 5.3: Administration interface for thesaurus

Upload Upload the selected rdf file to the node. Then it will list all thesaurus available on the node.

5.4 Editing/browsing thesaurus : add/remove/browse keywords

>From the thesaurus administration interface, click on the edit button for a local thesaurus or the view button for an external thesaurus. This interface allows :

- keywords search
- add/remove keywords for local thesaurus.

Use the textbox and the type of search in order to search for keywords.

5.5 Metadata editing : adding keywords

When editing metadata in ISO or Dublin core, the keyword fields autocomplete when editor fill the fields. Keywords available in all thesaurus know by the current node are returned. Editor could select one of the list or could type any other keywords.




Figure 5.4: Keyword description




Figure 5.5: Administration interface for thesaurus




Figure 5.6: Administration interface for thesaurus

5.6 Search criteria : keywords

In the advanced search interface, the keyword field will proposed all keywords used in the metadata. These keywords are indexed by Lucene on creation/update of metadata. The number of metadata linked to all keywords available in the index are display. User could type in the keyword field or click the icon to get the list of keywords available.

Part II

GAST

Chapter 6

Introduction

6.1 What is GAST?

GAST stands for "GeoNetwork's Administrator Survival Tool" and is a standalone application whose purpose is to simplify some low level tasks like change of the servlet, configuration of the JDBC account, setup the database and so on. Most of the GAST's facilities work only for the GeoNetwork's installation where GAST is in. This implies that if you are using a servlet container other than Jetty (like Tomcat) you will not be able to change some options (like the servlet's name). Other facilities work for any servlet container but you have to specify the GeoNetwork's URL into the GAST's configuration dialog.

6.2 Starting GAST

GAST belongs to the core components so it is installed by default. It is located into the **gast** folder and to start it you can either use the **java** command or just click its jar's icon. To use the java command you have to:

- from the GeoNetwork's root folder, issue the command:

```
java -jar gast/gast.jar
```

- from the gast folder, issue the command:

```
java -jar gast.jar
```

To use your window manager, simply open the GeoNetwork's folder, go inside the **gast** folder and click the **gast.jar** icon. If you have Java installed, GAST should start in a few seconds.

To run, GAST needs at least Java 1.5. It will not work on Java 1.4 and it should run on Java 1.6 (anyway, it has not been tested).







Figure 6.1: GAST's main window with a tool selected

6.3 Operating modes

When you start GAST, you get an application window like the one in figure 6.1. On the left side you have a panel with the tools you can use. After selecting a tool, on the right side you get the tool's options panel.

Every GAST tool has an **operating mode**, which defines the condition under which the tool can be used. The tool's mode is shown with an icon on the right side of the tool's name. The operating modes, with their icons are summarized in the following table:

Mode	Icon	Description
Restarted		The tool can be always used, but GeoNetwork must be restarted in order to make the change effective.
Running		The tool can be used only if GeoNetwork is running.
Stopped		The tool can be used only if GeoNetwork is stopped. This is important because some tools change the database's account or create the database from scratch. These are sensitive operations that cannot be performed while GeoNetwork is running.




Figure 6.2: The configuration dialog

6.4 Tools subdivision

All GAST tools present into the left panel are logically subdivided into groups. Each group represents a GeoNetwork's aspect for which GAST allows you a graphic interface. The groups are:

Configuration You can change some configuration parameters, like the servlet's name, JDBC account etc...

Management General purpose tools related to the site's administration.

Database Operations that regard the database. Here you can find tools to create a database from scratch, creating the schema and filling it with proper data.

Migration Tools that allow you to migrate metadata from old installation.

6.5 Configuration dialog

Some of the GAST's tools access a running GeoNetwork. Usually, GAST connects to GeoNetwork using the connection parameters it finds on the installation folder but you can specify other parameters in order to connect to other instances. This is mandatory when the GeoNetwork instance is not running on the embedded Jetty server. In addition to that, some tools require authentication so account parameters must be provided.

To provide these parameters, you have to use the GAST's configuration dialog. To open the dialog, simply select **Options** ▸ **Config** from the menubar. You will get the dialog shown in figure 6.2.

The dialog is subdivided into 2 areas:

- Server** Tells GAST how to connect to a running GeoNetwork. If you select the **embedded** option, GAST will get the connection parameters from the installation directory. Alternatively, if you use Tomcat or an external servlet container you have to choose the **external** option and provide the connection parameters yourself. Remember that this will work only for tools which operating mode is *Running*. For all the others, GAST will access the parameters from the installation directory.
- Account** Some tools require authentication. To authenticate, simply select the **Use this account** option and provide the username and password of a valid account. These parameters will work for both the embedded instance and for any external instance.

Chapter 7

Import / export tools

7.1 Introduction

Using GAST, you can import and export metadata as will. These facilities allow you a broad variety of tasks:

- Backup of the entire metadata set. Each metadata has its own file with maps and other data files. Once you have the backup, you can decide to import all or only some of them.
- Move your metadata from one GeoNetwork's installation to another. This can be done to mirror your metadata or to upgrade an old installation. In the last case, you export your metadata from your old installation and then reimport them into the new one.
- Fill the system with test data. Using the 'skip uuid' option, you can reimport the same metadata over and over again. This is usefull, for example, if you want to perform stress tests.

Metadata are exported using the MEF format.

7.2 Export

This facility is located inside the **Management** node on the left panel and allows you to export a set of metadata using the MEF format. Clicking the **Export** node you get its option panel on the right, as you can see from figure 7.1.

Here follows a detailed explanation of the options:




Figure 7.1: The metadata export panel

Output folder This is the target folder in your system where GAST will put the exported metadata. You can either press the Browse button to navigate through your file system to choose a better location or enter it manually into the textfield.

Format Here you can specify the metadata's output format. See the MEF specification for more information.

Skip UUID Normally is not selected. If you select it, you will loose the metadata's unique identifier (uuid) but you will be able to reimport that metadata over and over again. This is usefull to fill the system with test data.

Search This panel contains some search criteria that you can enter when exporting metadata.

Please notice that the export's result will depend on the metadata visible to the searching user. If you do not authenticate, you will get only public metadata.

Pressing the Export button will start the process. A progress dialog will be opened to show the export status.

7.3 Import

This facility is located inside the **Management** node on the left panel and allows you to import a set of metadata that have been previously exported using the export facility described above. Clicking the **Import** node you get its option panel on the right, as you can see from figure 7.2.




Figure 7.2: The metadata import panel

Here follows a detailed explanation of the options:

Input folder This is the source folder in your system that GAST will scan to collect metadata to import. GAST will try to import all files with the **mef** extension. Please notice that subfolders are not scanned. You can either press the Browse button to navigate through your file system to choose a better location or enter it manually into the textfield.

Pressing the Export button will start the process. A progress dialog will be opened to show the import status.

7.4 A note on ownership

Please, consider that the MEF format version 1.0 does not take into account user and group ownership. When exporting metadata, you lose this information. When importing metadata, the new owner becomes the user that is performing the import while the group ownership is set to null.