

# **Squirrel 2.2 Reference Manual**

**version 2.2 stable**

**Alberto Demichelis**

---

## **Squirrel 2.2 Reference Manual: version 2.2 stable**

Alberto Demichelis

Extensive review: Wouter Van Oortmersern

Copyright © 2003-2008 Alberto Demichelis

This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software.

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

1. The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
  2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
  3. This notice may not be removed or altered from any source distribution.
-

---

---

---

# Table of Contents

1. Introduction .....	1
2. The language .....	2
Lexical structure .....	2
Identifiers .....	2
Keywords .....	2
Operators .....	2
Other tokens .....	2
Literals .....	2
Comments .....	3
Values and Data types .....	3
Integer .....	4
Float .....	4
String .....	4
Null .....	4
Bool .....	5
Table .....	5
Array .....	5
Function .....	5
Class .....	5
Class instance .....	5
Generator .....	6
Userdata .....	6
Thread .....	6
Weak References .....	6
Execution Context .....	6
Variables .....	6
Statements .....	8
Block .....	8
Control Flow Statements .....	8
Loops .....	9
break .....	10
continue .....	10
return .....	10
yield .....	11
Local variables declaration .....	11
Function declaration .....	11
Class declaration .....	11
try/catch .....	11
throw .....	12
const .....	12
enum .....	12
expression statement .....	12
Expressions .....	12
Assignment(=) & new slot(<-) .....	12
Operators .....	13
Table constructor .....	15
delegate .....	16
clone .....	16
Array constructor .....	17
Tables .....	17
Construction .....	17
Slot creation .....	17
Slot deletion .....	18

---

Arrays .....	18
Functions .....	18
Function declaration .....	18
Function calls .....	20
Binding an environment to a function .....	20
Free variables .....	21
Tail recursion .....	21
Classes .....	21
Class declaration .....	21
Class instances .....	24
Inheritance .....	25
Metamethods .....	27
Generators .....	27
Constants & Enumerations .....	28
Constants .....	28
Enumerations .....	29
Implementation notes .....	29
Threads .....	30
Using threads .....	30
Weak References .....	32
Delegation .....	33
Metamethods .....	33
_set .....	34
_get .....	34
_newslot .....	34
_delslot .....	34
_add .....	35
_sub .....	35
_mul .....	35
_div .....	35
_modulo .....	35
_unm .....	35
_typeof .....	35
_cmp .....	35
_call .....	36
_cloned .....	36
_nexti .....	36
_tostring .....	36
_inherited .....	36
_newmember .....	36
Built-in functions .....	37
Global symbols .....	37
Default delegates .....	38
3. Embedding Squirrel .....	45
Memory management .....	45
Unicode .....	45
Squirrel on 64 bits architectures .....	45
Error conventions .....	45
Initializing Squirrel .....	46
The Stack .....	46
Stack indexes .....	46
Stack manipulation .....	46
Runtime error handling .....	48
Compiling a script .....	48
Calling a function .....	49
Create a C function .....	50
Tables and arrays manipulation .....	51
Userdata and UserPointers .....	53

---

The registry table .....	53
Maintaining strong references to Squirrel values from the C API .....	53
Debug Interface .....	54
4. API Reference .....	56
Virtual Machine .....	56
Compiler .....	61
Stack Operations .....	63
Object creation and handling .....	65
Calls .....	77
Objects manipulation .....	80
Bytecode serialization .....	88
Raw object handling .....	89
Debug interface .....	92
Index .....	94

---

# Chapter 1. Introduction

Squirrel is a high level imperative-OO programming language, designed to be a powerful scripting tool that fits in the size, memory bandwidth, and real-time requirements of applications like games. Although Squirrel offers a wide range of features like dynamic typing, delegation, higher order functions, generators, tail recursion, exception handling, automatic memory management, both compiler and virtual machine fit together in about 6k lines of C++ code.

---

# Chapter 2. The language

This part of the document describes the syntax and semantics of the language.

## Lexical structure

### Identifiers

Identifiers start with a alphabetic character or '\_' followed by any number of alphabetic characters, '\_' or digits ([0-9]). Squirrel is a case sensitive language, this means that the lowercase and uppercase representation of the same alphabetic character are considered different characters. For instance "foo", "Foo" and "fOo" will be treated as 3 distinct identifiers.

$id := [a-zA-Z\_][a-zA-Z\_0-9]^*$

### Keywords

The following words are reserved words by the language and cannot be used as identifiers:

break	case	catch	class	clone	continue
const	default	delegate	delete	else	enum
extends	for	function	if	in	local
null	resume	return	switch	this	throw
try	typeof	while	parent	yield	constructor
vargc	vargv	instanceof	true	false	static

Keywords are covered in detail later in this document.

### Operators

Squirrel recognizes the following operators:

!	!=		==	&&	<=	=>	>
+	+=	-	-=	/	/=	*	*=
%	%=	++	--	<-	=	&	^
	~	>>	<<	>>>			

### Other tokens

Other used tokens are:

{    }    [    ]    .    :    ::    '    ;    "    @"

### Literals



Squirrel accepts integer numbers, floating point numbers and strings literals.

34	Integer number(base 10)
0xFF00A120	Integer number(base 16)
0753	Integer number(base 8)
'a'	Integer number
1.52	Floating point number
1.e2	Floating point number
1.e-2	Floating point number
"I'm a string"	String
@ "I'm a verbatim string"	String
@ " I'm a multiline verbatim string "	String

```
IntegerLiteral := [0-9]+ | '0x' [0-9A-Fa-f]+ | ''' [.]+ ''' | 0[0-7]+
FloatLiteral  := [0-9]+ '.' [0-9]+
FloatLiteral  := [0-9]+ '.' 'e'|'E' '+'|'-' [0-9]+
StringLiteral := '''[.]* '''
VerbatimStringLiteral := '@''''[.]* ''''
```

## Comments

A comment is text that the compiler ignores but that is useful for programmers. Comments are normally used to embed annotations in the code. The compiler treats them as white space.

The `/*` (slash, asterisk) characters, followed by any sequence of characters (including new lines), followed by the `*/` characters. This syntax is the same as ANSI C.

```
/*
this is
a multiline comment.
this lines will be ignored by the compiler
*/
```

The `//` (two slashes) characters, followed by any sequence of characters. A new line not immediately preceded by a backslash terminates this form of comment. It is commonly called a "single-line comment."

```
//this is a single line comment. this line will be ignored by the compiler
```

## Values and Data types

Squirrel is a dynamically typed language so variables do not have a type, although they refer to a value

that does have a type. Squirrel basic types are integer, float, string, null, table, array, function, generator, class, instance, bool, thread and userdata.

## Integer

An Integer represents a 32 bits (or better) signed number.

```
local a = 123 //decimal
local b = 0x0012 //hexadecimal
local c = 075 //octal
local d = 'w' //char code
```

## Float

A float represents a 32 bits (or better) floating point number.

```
local a=1.0
local b=0.234
```

## String

Strings are an immutable sequence of characters to modify a string is necessary create a new one.

Squirrel's strings, behave like C or C++, are delimited by quotation marks(") and can contain escape sequences(`\t`,`\a`,`\b`,`\n`,`\r`,`\v`,`\f`,`\|`,`\'`,`\0`,`\xhhh`).

Verbatim string literals begin with `@` and end with the matching quote. Verbatim string literals also can extend over a line break. If they do, they include any white space characters between the quotes:

```
local a = "I'm a wonderful string\n"
// has a newline at the end of the string
local x = @"I'm a verbatim string\n"
// the \n is copied in the string same as \\n in a regular string "I'm a verbatim
```

The only exception to the "no escape sequence" rule for verbatim string literals is that you can put a double quotation mark inside a verbatim string by doubling it:

```
local multiline = @"
    this is a multiline string
    it will ""embed"" all the new line
    characters
"
```

## Null

The null value is a primitive value that represents the null, empty, or non-existent reference. The type Null has exactly one value, called null.

```
local a=null
```

## Bool

the bool data type can have only two. They are the literals `true` and `false`. A bool value expresses the validity of a condition (tells whether the condition is true or false).

```
local a = true;
```

## Table

Tables are associative containers implemented as pairs of key/value (called a slot).

```
local t={}
local test=
{
  a=10
  b=function(a) { return a+1; }
}
```

## Array

Arrays are simple sequence of objects, their size is dynamic and their index starts always from 0.

```
local a=["I'm", "an", "array"]
local b=[null]
b[0]=a[2];
```

## Function

Functions are similar to those in other C-like languages and to most programming languages in general, however there are a few key differences (see below).

## Class

Classes are associative containers implemented as pairs of key/value. Classes are created through a 'class expression' or a 'class statement'. class members can be inherited from another class object at creation time. After creation members can be added until a instance of the class is created.

## Class instance

Class instances are created by calling a `class` object. Instances, as tables, are implemented as pair of key/value. Instances members cannot be dynamically added or removed however the value of the members can be changed.

## Generator

Generators are functions that can be suspended with the statement 'yield' and resumed later (see Generators).

## Userdata

Userdata objects are blobs of memory(or pointers) defined by the host application but stored into Squirrel variables (See Userdata and UserPointers).

## Thread

Threads are objects that represents a cooperative thread of execution, also known as coroutines.

## Weak References

Weak References are objects that point to another(non scalar) object but do not own a strong reference to it. (See Weak References).

## Execution Context

The execution context is the union of the function stack frame and the function environment object(this). The stack frame is the portion of stack where the local variables declared in its body are stored. The environment object is an implicit parameter that is automatically passed by the function caller (see Functions). During the execution, the body of a function can only transparently refer to his execution context. This mean that a single identifier can refer either to a local variable or to an environment object slot; Global variables require a special syntax (see Variables). The environment object can be explicitly accessed by the keyword this.

## Variables

There are two types of variables in Squirrel, local variables and tables/arrays slots. Because global variables are stored in a table, they are table slots.

A single identifier refers to a local variable or a slot in the environment object.

```
derefexp := id;
```

```
_table["foo"]  
_array[10]
```

with tables we can also use the '.' syntax

```
derefexp := exp '.' id
```

```
_table.foo
```

Squirrel first checks if an identifier is a local variable (function arguments are local variables) if not it checks if it is a member of the environment object (this).

For instance:

```
function testy(arg)
{
    local a=10;
    print(a);
    return arg;
}
```

will access to local variable 'a' and prints 10.

```
function testy(arg)
{
    local a=10;
    return arg+foo;
}
```

in this case 'foo' will be equivalent to 'this.foo' or this["foo"].

Global variables are stored in a table called the root table. Usually in the global scope the environment object is the root table, but to explicitly access the global table from another scope, the slot name must be prefixed with '::' (::foo).

```
exp:= '::' id
```

For instance:

```
function testy(arg)
{
    local a=10;
    return arg+::foo;
}
```

accesses the global variable 'foo'.

However (since squirrel 2.0) if a variable is not local and is not found in the 'this' object Squirrel will search it in the root table.

```
function test() {
    foo = 10;
}
```

is equivalent to write

```
function test() {
    if("foo" in this) {
        this.foo = 10;
    }else {
        ::foo = 10;
    }
}
```

# Statements

A squirrel program is a simple sequence of statements.

```
stats := stat [';' | '\n'] stats
```

Statements in squirrel are comparable to the C-Family languages (C/C++, Java, C# etc...): assignment, function calls, program flow control structures etc.. plus some custom statement like *yield*, *table* and *array* constructors (All those will be covered in detail later in this document). Statements can be separated with a new line or ';' (or with the keywords *case* or *default* if inside a *switch/case* statement), both symbols are not required if the statement is followed by '}'.

## Block

```
stat := '{' stats '}'
```

A sequence of statements delimited by curly brackets ({ }) is called block; a block is a statement itself.

## Control Flow Statements

squirrel implements the most common control flow statements: *if*, *while*, *do-while*, *switch-case*, *for*, *foreach*.

### true and false

Squirrel has a boolean type(*bool*) however like C++ it considers *null*, *0*(integer) and *0.0*(float) as *false*, any other value is considered *true*.

### if/else

```
stat:= 'if' '(' exp ')' stat ['else' stat]
```

Conditionally execute a statement depending on the result of an expression.

```
if(a>b)
    a=b;
else
    b=a;
////
if(a==10)
{
    b=a+b;
    return a;
}
```

### while

```
stat:= 'while' '(' exp ')' stat
```

Executes a statement until the condition is false.

```
function testy(n)
{
    local a=0;
    while(a<n) a+=1;

    while(1)
    {
        if(a<0) break;
        a-=1;
    }
}
```

## do/while

*stat := 'do' stat 'while' '(' expression ')'*

Executes a statement once, and then repeats execution of the statement until a condition expression evaluates to false.

```
local a=0;
do
{
    print(a+"\n");
    a+=1;
} while(a>100)
```

## switch

*stat := 'switch' '(' exp ')' '{'*  
*'case' case\_exp ':'*  
*stats*  
*['default' ':'*  
*stats]*  
*'}'*

Is a control statement allows multiple selections of code by passing control to one of the case statements within its body. The control is transferred to the case label whose case\_exp matches with exp if none of the case match will jump to the default label (if present). A switch statement can contain any number of case instances, if 2 case have the same expression result the first one will be taken in account first. The default label is only allowed once and must be the last one. A break statement will jump outside the switch block.

## Loops

### for

*stat := 'for' '(' [initexp] ';' [condexp] ';' [incexp] ')' statement*

Executes a statement as long as a condition is different than false.

```
for(local a=0;a<10;a+=1)
  print(a+"\n");
//or
glob <- null
for(glob=0;glob<10;glob+=1){
  print(glob+"\n");
}
//or
for(;;){
  print(loops forever+"\n");
}
```

## foreach

*'foreach' '(' [index\_id',' ] value\_id 'in' exp ')' stat*

Executes a statement for every element contained in an array, table, class, string or generator. If exp is a generator it will be resumed every iteration as long as it is alive; the value will be the result of 'resume' and the index the sequence number of the iteration starting from 0.

```
local a=[10,23,33,41,589,56]
foreach(idx,val in a)
  print("index="+idx+" value="+val+"\n");
//or
foreach(val in a)
  print("value="+val+"\n");
```

## break

*stat := 'break'*

The break statement terminates the execution of a loop (for, foreach, while or do/while) or jumps out of switch statement;

## continue

*stat := 'continue'*

The continue operator jumps to the next iteration of the loop skipping the execution of the following statements.

## return

*stat:= return [exp]*



The return statement terminates the execution of the current function/generator and optionally returns the result of an expression. If the expression is omitted the function will return null. If the return statement is used inside a generator, the generator will not be resumable anymore.

## yield

```
stat := yield [exp]
```

(see Generators).

## Local variables declaration

```
initz := id [= exp][', ' initz]  
stat := 'local' initz
```

Local variables can be declared at any point in the program; they exist between their declaration to the end of the block where they have been declared. EXCEPTION: a local declaration statement is allowed as first expression in a for loop.

```
for(local a=0;a<10;a+=1)  
    print(a);
```

## Function declaration

```
funcname := id ['::' id]  
stat := 'function' id ['::' id] + '(' args ')' ['::' '(' args ')'] stat
```

creates a new function.

## Class declaration

```
memberdecl := id '=' exp [';'] | '[' exp ']' '=' exp [';'] | functionstat | 'const'  
stat := 'class' derefexp ['extends' derefexp] '{'  
        [memberdecl]  
        '}'
```

creates a new class.

## try/catch

```
stat := 'try' stat 'catch' '(' id ')' stat
```

The try statement encloses a block of code in which an exceptional condition can occur, such as a runtime error or a throw statement. The catch clause provides the exceptionhandling code. When a catch

clause catches an exception, its id is bound to that exception.

## throw

*stat := 'throw' exp*

Throws an exception. Any value can be thrown.

## const

*stat := 'const' id '=' Integer | Float | StringLiteral*

Declares a constant (see Constants & Enumerations).

## enum

*enumerations := ( 'id' '=' Integer | Float | StringLiteral ) [' ','']  
stat := 'enum' id '{' enumerations '}'*

Declares an enumeration (see Constants & Enumerations).

## expression statement

*stat := exp*

In Squirrel every expression is also allowed as statement, if so, the result of the expression is thrown away.

# Expressions

## Assignment(=) & new slot(<-)

*exp := derefexp '=' exp  
exp := derefexp '<-' exp*

squirrel implements 2 kind of assignment: the normal assignment(=)

*a=10;*

and the "new slot" assignment.

*a <- 10;*

The new slot expression allows to add a new slot into a table(see Tables). If the slot already exists in the table it behaves like a normal assignment.

## Operators

### ?: Operator

*exp* := *exp\_cond* '?' *exp1* ':' *exp2*

conditionally evaluate an expression depending on the result of an expression.

### Arithmetic

*exp* := '*exp*' *op* '*exp*'

Squirrel supports the standard arithmetic operators +, -, \*, / and %. Other than that it also supports compact operators (+=, -=, \*=, /=, %=) and increment and decrement operators(++ and --);

```
a+=2;
//is the same as writing
a=a+2;
x++
//is the same as writing
x=x+1
```

All operators work normally with integers and floats; if one operand is an integer and one is a float the result of the expression will be float. The + operator has a special behavior with strings; if one of the operands is a string the operator + will try to convert the other operand to string as well and concatenate both together. For instances and tables, `_tostring` is invoked.

### Relational

*exp* := '*exp*' *op* '*exp*'

Relational operators in Squirrel are : == < <= > >= !=

These operators return null if the expression is false and a value different than null if the expression is true. Internally the VM uses the integer 1 as true but this could change in the future.

### Logical

*exp* := *exp* *op* *exp*  
*exp* := '!' *exp*

Logical operators in Squirrel are : && || !

The operator && (logical and) returns null if its first argument is null, otherwise returns its second argument. The operator || (logical or) returns its first argument if it is different than null, otherwise returns the second argument.

The '!' operator will return null if the given value to negate was different than null, or a value different than null if the given value was null.

## in operator

*exp := keyexp 'in' tableexp*

Tests the existence of a slot in a table. Returns a value different than null if keyexp is a valid key in tableexp

```
local t=
{
    foo="I'm foo",
    [123]="I'm not foo"
}

if("foo" in t) dostuff("yep");
if(123 in t) dostuff();
```

## instanceof operator

*exp := instanceexp 'instanceof' classexp*

Tests if a class instance is an instance of a certain class. Returns a value different than null if instanceexp is an instance of classexp.

## typeof operator

*exp := 'typeof' exp*

returns the type name of a value as string.

```
local a={},b="squirrel"
print(typeof a); //will print "table"
print(typeof b); //will print "string"
```

## comma operator

*exp := exp ',' exp*

The comma operator evaluates two expression left to right, the result of the operator is the result of the expression on the right; the result of the left expression is discarded.

```
local j=0,k=0;
for(local i=0; i<10; i++ , j++)
{
    k = i + j;
}
```

```
local a,k;
a = (k=1,k+2); //a becomes 3
```

## Bitwise Operators

```
exp := 'exp' op 'exp'
exp := '~' exp
```

Squirrel supports the standard c-like bit wise operators `&,&|,&^,&~,<<,>>` plus the unsigned right shift operator `>>>`. The unsigned right shift works exactly like the normal right shift operator(`>>`) except for treating the left operand as an unsigned integer, so is not affected by the sign. Those operators only work on integers values, passing of any other operand type to these operators will cause an exception.

## Operators precedence

<code>-,~,!,typeof,++,--</code>	highest
<code>/,*,%</code>	...
<code>+, -</code>	
<code>&lt;&lt;, &gt;&gt;, &gt;&gt;&gt;</code>	
<code>&lt;, &lt;=, &gt;, &gt;=</code>	
<code>==, !=</code>	
<code>&amp;</code>	
<code>^</code>	
<code> </code>	
<code>&amp;&amp;, in</code>	
<code>  </code>	
<code>?:</code>	...
<code>+=,=,--</code>	
<code>,(comma operator)</code>	lowest

## Table constructor

```
tslots := ( 'id' '=' exp | '[' exp ']' '=' exp ) [',']
exp := '{' [tslots] '}'
```

Creates a new table.

```
local a={} //create an empty table
```

A table constructor can also contain slots declaration; With the syntax:

```
id = exp [',']
```

a new slot with id as key and exp as value is created

```
local a=
{
    slot1="I'm the slot value"
}
```

An alternative syntax can be

```
'[' exp1 ']' = exp2 [',']
```

A new slot with exp1 as key and exp2 as value is created

```
local a=
{
    [1]="I'm the value"
}
```

both syntaxes can be mixed

```
local table=
{
    a=10,
    b="string",
    [10]={},
    function bau(a,b)
    {
        return a+b;
    }
}
```

The comma between slots is optional.

## delegate

```
exp:= 'delegate' parentexp : exp
```

Sets the parent of a table. The result of parentexp is set as parent of the result of exp, the result of the expression is exp (see Delegation).

## clone

```
exp:= 'clone' exp
```

Clone performs shallow copy of a table, array or class instance (copies all slots in the new object without recursion). If the source table has a delegate, the same delegate will be assigned as delegate (not

copied) to the new table (see Delegation).

After the new object is ready the “\_cloned” meta method is called (see Metamethods).

When a class instance is cloned the constructor is not invoked (initializations must rely on \_cloned instead)

## Array constructor

```
exp := '[' [explist] ']
```

Creates a new array.

```
a <- [] //creates an empty array
```

arrays can be initialized with values during the construction

```
a <- [1,"string!",[],{}] //creates an array with 4 elements
```

## Tables

Tables are associative containers implemented as pairs of key/value (called slot); values can be any possible type and keys any type except 'null'. Tables are squirrel's skeleton, delegation and many other features are all implemented through this type; even the environment, where global variables are stored, is a table (known as root table).

## Construction

Tables are created through the table constructor (see Table constructor)

## Slot creation

Adding a new slot in a existing table is done through the "new slot" operator '<-'; this operator behaves like a normal assignment except that if the slot does not exists it will be created.

```
local a={}
```

The following line will cause an exception because the slot named 'newslot' does not exist in the table 'a'

```
a.newslot = 1234
```

this will succeed:

```
a.news1ot <- 1234;
```

or

```
a[1] <- "I'm the value of the new slot";
```

## Slot deletion

*exp := delete derefexp*

Deletion of a slot is done through the keyword `delete`; the result of this expression will be the value of the deleted slot.

```
a <- {
  test1=1234
  deleteme="now"
}

delete a.test1
print(delete a.deleteme); //this will print the string "now"
```

## Arrays

An array is a sequence of values indexed by a integer number from 0 to the size of the array minus 1. Arrays elements can be obtained through their index.

```
local a=["I'm a string", 123]
print(typeof a[0]) //prints "string"
print(typeof a[1]) //prints "integer"
```

Resizing, insertion, deletion of arrays and arrays elements is done through a set of standard functions (see built-in functions).

## Functions

Functions are first class values like integer or strings and can be stored in table slots, local variables, arrays and passed as function parameters. Functions can be implemented in Squirrel or in a native language with calling conventions compatible with ANSI C.

## Function declaration

Functions are declared through the function expression

```
local a= function(a,b,c) {return a+b-c;}
```



or with the syntactic sugar

```
function ciao(a,b,c)
{
  return a+b-c;
}
```

that is equivalent to

```
this.ciao <- function(a,b)
{
  return a+b-c;
}
```

is also possible to declare something like

```
T <- {}
function T::ciao(a,b,c)
{
  return a+b-c;
}

//that is equivalent to write

T.ciao <- function(a,b,c)
{
  return a+b-c;
}

//or

T <- {
  function ciao(a,b,c)
  {
    return a+b-c;
  }
}
```

## Default Paramaters

Squirrel's functions can have default parameters.

A function with default parameters is declared as follows:

```
function test(a,b,c = 10, d = 20)
{
  ....
}
```

when the function `test` is invoked and the parameter `c` or `d` are not specified, the VM automatically as-

signs the default value to the unspecified parameter. A default parameter can be any valid squirrel expression. The expression is evaluated at runtime.

## Function with variable number of paramaters

Squirrel's functions can have variable number of parameters(varargs functions).

A vararg function is declared by adding three dots (`...`) at the end of its parameter list.

When the function is called all the extra parameters will be accessible through the *pseudo array* called `vargv`.

`vargv` can only indexed with a numeric object(float or integer). The number of parameter contained in `vargv` is stored in the *pseudo variable* `vargc`.

*Note that `vargv` is not a real object, it can't be assigned or passed as parameter.*

```
function test(a,b,...)
{
    for(local i = 0; i< argc; i++)
    {
        ::print("varparam "+i+" = "+vargv[i]+"\\n");
    }
}

test("goes in a","goes in b",0,1,2,3,4,5,6,7,8);
```

## Function calls

*exp := derefexp '(' explist ')'*

The expression is evaluated in this order: derefexp after the explist (arguments) and at the end the call.

Every function call in Squirrel passes the environment object 'this' as hidden parameter to the called function. The 'this' parameter is the object where the function was indexed from.

If we call a function with this syntax

```
table.foo(a)
```

the environment object passed to foo will be 'table'

```
foo(x,y) // equivalent to this.foo(x,y)
```

The environment object will be 'this' (the same of the caller function).

## Binding an environment to a function

while by default a squirrel function call passes as environment object 'this', the object where the function was indexed from. However, is also possible to statically bind an environment to a closure using the built-in method `closure.bindenv(env_obj)`. The method `bindenv()` returns a new instance of a closure with the environment bound to it. When an environment object is bound to a function, every time the

function is invoked, its 'this' parameter will always be the previously bound environment. This mechanism is useful to implement callbacks systems similar to C# delegates.

### Note

The closure keeps a weak reference to the bound environment object, because of this if the object is deleted, the next call to the closure will result in a null environment object.

## Free variables

Free variables are variables referenced by a function that are not visible in the function scope. In the following example the function `foo()` declares `x`, `y` and `testy` as free variables.

```
local x=10,y=20
testy <- "I'm testy"

function foo(a,b):(x,y,testy)
{
  ::print(testy);
  return a+b+x+y;
}
```

The value of a free variable is frozen and bound to the function when the function is created; the value is passed to the function as implicit parameter every time it is called.

## Tail recursion

Tail recursion is a method for partially transforming a recursion in a program into an iteration: it applies when the recursive calls in a function are the last executed statements in that function (just before the return). If this happens the squirrel interpreter collapses the caller stack frame before the recursive call; because of that very deep recursions are possible without risk of a stack overflow.

```
function loopy(n)
{
  if(n>0){
    ::print("n="+n+"\n");
    return loopy(n-1);
  }
}

loopy(1000);
```

## Classes

Squirrel implements a class mechanism similar to languages like Java/C++/etc... however because of its dynamic nature it differs in several aspects. Classes are first class objects like integer or strings and can be stored in table slots local variables, arrays and passed as function parameters.

## Class declaration

A class object is created through the keyword 'class'. The class object follows the same declaration syntax of a table(see tables) with the only difference of using ';' as optional separator rather than ','.

For instance:

```
class Foo {
  //constructor
  constructor(a)
  {
    testy = ["stuff",1,2,3];
  }
  //member function
  function PrintTesty()
  {
    foreach(i,val in testy)
    {
      ::print("idx = "+i+" = "+val+" \n");
    }
  }
  //property
  testy = null;
}
```

the previous code examples is a syntactic sugar for:

```
Foo <- class {
  //constructor
  constructor(a)
  {
    testy = ["stuff",1,2,3];
    testy = a;
  }
  //member function
  function PrintTesty()
  {
    foreach(i,val in testy)
    {
      ::print("idx = "+i+" = "+val+" \n");
    }
  }
  //property
  testy = null;
}
```

in order to emulate namespaces, is also possible to declare something like this

```
//just 2 regular nested tables
FakeNamespace <- {
  Utils = {}
}

class FakeNamespace.Utils.SuperClass {
  constructor()
  {
    ::print("FakeNamespace.Utils.SuperClass")
  }
  function DoSomething()
  {
    ::print("DoSomething()")
  }
}
```

```
function FakeNamespace::Utils::SuperClass::DoSomethingElse()  
{  
    ::print("FakeNamespace::Utils::SuperClass::DoSomethingElse()")  
}  
  
local testy = FakeNamespace.Utils.SuperClass();  
testy.DoSomething();  
testy.DoSomethingElse();
```

After its declaration, methods or properties can be added or modified by following the same rules that apply to a table(operator <- and =).

```
//adds a new property  
Foo.stuff <- 10;  
  
//modifies the default value of an existing property  
Foo.testy = "I'm a string";  
  
//adds a new method  
function Foo::DoSomething(a,b)  
{  
    return a+b;  
}
```

After a class is instantiated is no longer possible to add new properties or methods to it.

## Static variables

Squirrel's classes support static member variables. A static variable shares its value between all instances of the class. Statics are declared by prefixing the variable declaration with the keyword `static`; the declaration must be in the class body.

### Note

Statics are read-only.

```
class Foo {  
    constructor()  
    {  
        //..stuff  
    }  
    name = "normal variable";  
    //static variable  
    static classname = "The class name is foo";  
};
```

## Class attributes

Classes allow to associate attributes to it's members. Attributes are a form of metadata that can be used to store application specific informations, like documentations strings, properties for IDEs, code generators etc... Class attributes are declared in the class body by preceding the member declaration and are delimited by the symbol </ and />. Here an example:

```
class Foo </ test = "I'm a class level attribute" />{  
    </ test = "freakin attribute" /> //attributes of PrintTesty  
    function PrintTesty()  
    {  
        foreach(i,val in testy)  
        {  
            ::print("idx = "+i+" = "+val+" \n");  
        }  
    }  
}
```

```
        }
    }
    </ flippy = 10 , second = [1,2,3] /> //attributes of testy
    testy = null;
}
```

Attributes are, matter of fact, a table. Squirrel uses `</ />` syntax instead of curly brackets `{ }` for the attribute declaration to increase readability.

This means that all rules that apply to tables apply to attributes.

Attributes can be retrieved through the built-in function `classobj.getattributes(membername)` (see built-in functions). and can be modified/added through the built-in function `classobj.setattributes(membername, val)`.

the following code iterates through the attributes of all Foo members.

```
foreach(member, val in Foo)
{
    ::print(member+"\n");
    local attr;
    if((attr = Foo.getattributes(member)) != null) {
        foreach(i, v in attr)
        {
            ::print("\t"+i+" = "+(typeof v)+"\n");
        }
    }
    else {
        ::print("\t<no attributes>\n")
    }
}
```

## Class instances

The class objects inherits several of the table's feature with the difference that multiple instances of the same class can be created. A class instance is an object that share the same structure of the table that created it but holds its own values. Class *instantiation* uses function notation. A class instance is created by calling a class object. Can be useful to imagine a class like a function that returns a class instance.

```
//creates a new instance of Foo
local inst = Foo();
```

When a class instance is created its members are initialized with the same value specified in the class declaration.

When a class defines a method called 'constructor', the class instantiation operation will automatically invoke it for the newly created instance. The constructor method can have parameters, this will impact on the number of parameters that the *instantiation operation* will require. Constructors as normal functions can have variable number of parameters (using the parameter `...`).

```
class Rect {
    constructor(w,h)
    {
        width = w;
        height = h;
    }
}
```

```
x = 0;
y = 0;
width = null;
height = null;
}

//Rect's constructor has 2 parameters so the class has to be 'called'
//with 2 parameters
local rc = Rect(100,100);
```

After an instance is created, its properties can be set or fetched following the same rules that apply to tables. Methods cannot be set.

Instance members cannot be removed.

The class object that created a certain instance can be retrieved through the built-in function `instance.getclass()` (see built-in functions)

The operator `instanceof` tests if a class instance is an instance of a certain class.

```
local rc = Rect(100,100);
if(rc instanceof ::Rect) {
    ::print("It's a rect");
}
else {
    ::print("It isn't a rect");
}
```

## Inheritance

Squirrel's classes support single inheritance by adding the keyword `extends`, followed by an expression, in the class declaration. The syntax for a derived class is the following:

```
class SuperFoo extends Foo {
    function DoSomething() {
        ::print("I'm doing something");
    }
}
```

When a derived class is declared, Squirrel first copies all base's members in the new class then proceeds with evaluating the rest of the declaration.

A derived class inherit all members and properties of it's base, if the derived class overrides a base function the base implementation is shadowed. It's possible to access a overridden method of the base class by fetching the method from the base class object.

Here an example:

```
class Foo {
    function DoSomething() {
        ::print("I'm the base");
    }
};

class SuperFoo extends Foo {
```

```

        //overridden method
        function DoSomething() {
            //calls the base method
            ::Foo.DoSomething();
            ::print("I'm doing something");
        }
    }

```

Same rule apply to the constructor. The constructor is a regular function (apart from being automatically invoked on construction).

```

class Base {
    constructor()
    {
        ::print("Base constructor\n");
    }
}

class Child extends Base {
    constructor()
    {
        ::Base.constructor();
        ::print("Child constructor\n");
    }
}

local test = Child();

```

The base class of a derived class can be retrieved through the keyword `parent`. `parent` is a 'pseudo slot'. The `parent` slot cannot be set.

```

local thebaseclass = SuperFoo.parent;

```

Note that because methods do not have special protection policies when calling methods of the same objects, a method of a base class that calls a method of the same class can end up calling a overridden method of the derived class.

```

class Foo {
    function DoSomething() {
        ::print("I'm the base");
    }
    function DoIt()
    {
        DoSomething();
    }
};

class SuperFoo extends Foo {
    //overridden method
    function DoSomething() {
        ::print("I'm the derived");
    }
    function DoIt() {
        ::Foo.DoIt();
    }
}

```



```
//creates a new instance of SuperFoo
local inst = SuperFoo();

//prints "I'm the derived"
inst.DoIt();
```

## Metamethods

Class instances allow the customization of certain aspects of their semantics through metamethods (see Metamethods). For C++ programmers: "metamethods behave roughly like overloaded operators". The metamethods supported by classes are `_add`, `_sub`, `_mul`, `_div`, `_unm`, `_modulo`, `_set`, `_get`, `_typeof`, `_nexti`, `_cmp`, `_call`, `_delslot`, `_tostring`

Class objects instead support only 2 metamethods: `_newmember` and `_inherited`. The following example shows how to create a class that implements the metamethod `_add`.

```
class Vector3 {
    constructor(...)
    {
        if(vargc >= 3) {
            x = vargv[0];
            y = vargv[1];
            z = vargv[2];
        }
    }
    function _add(other)
    {
        return ::Vector3(x+other.x,y+other.y,z+other.z);
    }

    x = 0;
    y = 0;
    z = 0;
}

local v0 = Vector3(1,2,3)
local v1 = Vector3(11,12,13)
local v2 = v0 + v1;
::print(v2.x+", "+v2.y+", "+v2.z+"\n");
```

Since version 2.1, classes support 2 metamethods `_inherited` and `_newmember`. `_inherited` is invoked when a class inherits from the one that implements `_inherited`. `_newmember` is invoked for each member that is added to the class (at declaration time).

## Generators

A function that contains a `yield` statement is called 'generator function'. When a generator function is called, it does not execute the function body, instead it returns a new suspended generator. The returned generator can be resumed through the `resume` statement while it is alive. The `yield` keyword, suspends the execution of a generator and optionally returns the result of an expression to the function that resumed the generator. The generator dies when it returns, this can happen through an explicit `return` statement or by exiting the function body; If an unhandled exception (or runtime error) occurs while a gener-

ator is running, the generator will automatically die. A dead generator cannot be resumed anymore.

```
function geny(n)
{
    for(local i=0;i<n;i+=1)
        yield i;
    return null;
}

local gtor=geny(10);
local x;
while(x=resume gtor) print(x+"\n");
```

the output of this program will be

```
0
1
2
3
4
5
6
7
8
9
```

generators can also be iterated using the `foreach` statement. When a generator is evaluated by `foreach`, the generator will be resumed for each iteration until it returns. The value returned by the `return` statement will be ignored.

## Constants & Enumerations

Squirrel allows to bind constant values to an identifier that will be evaluated compile-time. This is achieved through constants and enumerations.

### Constants

Constants bind a specific value to an identifier. Constants are similar to global values, except that they are evaluated compile time and their value cannot be changed.

constants values can only be integers, floats or string literals. No expression are allowed. are declared with the following syntax.

```
const foobar = 100;
const floatbar = 1.2;
const stringbar = "I'm a constant string";
```

constants are always globally scoped, from the moment they are declared, any following code can reference them. Constants will shadow any global slot with the same name( the global slot will remain visible

by using the `::` syntax).

```
local x = foobar * 2;
```

## Enumerations

As Constants, Enumerations bind a specific value to a name. Enumerations are also evaluated compile time and their value cannot be changed.

An enum declaration introduces a new enumeration into the program. Enumerations values can only be integers, floats or string literals. No expression are allowed.

```
enum Stuff {
  first, //this will be 0
  second, //this will be 1
  third //this will be 2
}
```

or

```
enum Stuff {
  first = 10
  second = "string"
  third = 1.2
}
```

An enum value is accessed in a manner that's similar to accessing a static class member. The name of the member must be qualified with the name of the enumeration, for example `Stuff.second`. Enumerations will shadow any global slot with the same name( the global slot will remain visible by using the `::` syntax).

```
local x = Stuff.first * 2;
```

## Implementation notes

Enumerations and Constants are a compile-time feature. Only integers, string and floats can be declared as `const/enum`; No expressions are allowed(because they would have to be evaluated compile time). When a `const` or an `enum` is declared, it is added compile time to the `consttable`. This table is stored in the VM shared state and is shared by the VM and all its threads. The `consttable` is a regular squir-

rel table; In the same way as the roottable it can be modified runtime. You can access the const-table through the built-in function `getconsttable()` and also change it through the built-in function `setconsttable()`

here some example:

```
//create a constant
getconsttable()["something"] <- 10"
//create an enumeration
getconsttable()["somethingelse"] <- { a = "10", c = "20", d = "200"};
//deletes the constant
delete getconsttable()["something"]
//deletes the enumeration
delete getconsttable()["somethingelse"]
```

This system allows to procedurally declare constants and enumerations, it is also possible to assign any squirrel type to a constant/enumeration(function, classes etc...). However this will make serialization of a code chunk impossible.

## Threads

Squirrel supports cooperative threads(also known as coroutines). A cooperative thread is a subroutine that can suspended in mid-execution and provide a value to the caller without returning program flow, then its execution can be resumed later from the same point where it was suspended. At first look a Squirrel thread can be confused with a generator, in fact their behaviour is quite similar. However while a generator runs in the caller stack and can suspend only the local routine stack a thread has its own execution stack, global table and error handler; This allows a thread to suspend nested calls and have it's own error policies.

## Using threads

Threads are created through the built-in function `'newthread(func)'`; this function gets as parameter a squirrel function and bind it to the new thread objects(will be the thread body). The returned thread object is initially in 'idle' state. the thread can be started with the function `'threadobj.call()'`; the parameters passed to 'call' are passed to the thread function.

A thread can be be suspended calling the function `suspend()`, when this happens the function that wokeup(or started) the thread returns (If a parameter is passed to `suspend()` it will be the return value of the wakeup function , if no parameter is passed the return value will be null). A suspended thread can be resumed calling the funtion `'threadobj.wakeup'`, when this happens the function that suspended the thread will return(if a parameter is passed to `wakeup` it will be the return value of the suspend function, if no parameter is passed the return value will be null).

A thread terminates when its main function returns or when an unhandled exception occurs during its execution.

```
function coroutine_test(a,b)
{
  ::print(a+" "+b+"\n");
  local ret = ::suspend("suspend 1");
  ::print("the coroutine says "+ret+"\n");
  ret = ::suspend("suspend 2");
  ::print("the coroutine says "+ret+"\n");
  ret = ::suspend("suspend 3");
}
```

```

        ::print("the coroutine says "+ret+"\n");
        return "I'm done"
    }

    local coro = ::newthread(coroutine_test);

    local susparam = coro.call("test","coroutine"); //starts the coroutine

    local i = 1;
    do
    {
        ::print("suspend passed ("+susparam+")\n");
        susparam = coro.wakeup("ciao "+i);
        ++i;
    }while(coro.getstatus()=="suspended")

    ::print("return passed ("+susparam+")\n")

```

the result of this program will be

```

test coroutine
suspend passed (suspend 1)
the coroutine says ciao 1
suspend passed (suspend 2)
the coroutine says ciao 2
suspend passed (suspend 3)
the coroutine says ciao 3
return passed (I'm done).

```

the following is an interesting example of how threads and tail recursion can be combined.

```

function statel()
{
    ::suspend("statel");
    return state2(); //tail call
}

function state2()
{
    ::suspend("state2");
    return state3(); //tail call
}

function state3()
{
    ::suspend("state3");
    return statel(); //tail call
}

local statethread = ::newthread(statel)

::print(statethread.call()+"\n");

for(local i = 0; i < 10000; i++)
    ::print(statethread.wakeup()+"\n");

```

## Weak References

The weak references allows the programmers to create references to objects without influencing the life-time of the object itself. In squirrel Weak references are first-class objects created through the built-in method `obj.weakref()`. All types except null implement the `weakref()` method; however in bools, integers and float the method simply returns the object itself (this because this types are always passed by value). When a weak references is assigned to a container (table slot, array, class or instance) is treated differently than other objects; When a container slot that hold a weak reference is fetched, it always returns the value pointed by the weak reference instead of the weak reference object. This allow the programmer to ignore the fact that the value handled is weak. When the object pointed by weak reference is destroyed, the weak reference is automatically set to null.

```
local t = {}  
local a = {"first", "second", "third"}  
//creates a weakref to the array and assigns it to a table slot  
t.thearray = a.weakref();
```

The table slot 'thearray' contains a weak reference to an array. The following line prints "first", because tables (and all other containers) always return the object pointed by a weak ref

```
print(t.thearray[0]);
```

the only strong reference to the array is owned by the local variable 'a', so because the following line assigns a integer to 'a' the array is destroyed.

```
a = 123;
```

When an object pointed by a weak ref is destroyed the weak ref is automatically set to null, so the following line will print "null".

```
:::print(typeof(t.thearray))
```

## Handling weak references explicitly

If a weak reference is assigned to a local variable, then is treated as any other value.

```
local t = {}  
local weakobj = t.weakref();
```

the following line prints "weakref".

```
:::print(typeof(weakobj))
```

the object pointed by the weakref can be obtained through the built-in method `weakref.ref()`.

The following line prints "table".

```
::print(typeof(weakobj.ref()))
```

## Delegation

Squirrel supports implicit delegation. Every table or userdata can have a parent table (delegate). A parent table is a normal table that allows the definition of special behaviors for his child. When a table (or userdata) is indexed with a key that doesn't correspond to one of its slots, the interpreter automatically delegates the get (or set) operation to its parent.

```
Entity <- {  
}  
  
function Entity::DoStuff()  
{  
    ::print(_name);  
}  
  
local newentity=delegate Entity : {  
    _name="I'm the new entity"  
}  
  
newentity.DoStuff(); //prints "I'm the new entity"
```

The parent of a table can be retrieved through keyword `parent`. `parent` is a 'pseudo slot'. The parent slot cannot be set, the `delegate` statement has to be used instead.

```
local thedelegate = newentity.parent;
```

## Metamethods

Metamethods are a mechanism that allows the customization of certain aspects of the language semantics. Those methods are normal functions placed in a table parent(delegate) or class declaration; It's possible to change many aspects of a table/class instance behavior by just defining a metamethod. Class objects(not instances) supports only 2 metamethods `_newmember`, `_inherited`.

For example when we use relational operators other than `'=='` on 2 tables, the VM will check if the table has a method in his parent called `'_cmp'` if so it will call it to determine the relation between the tables.

```
local comparable={  
    _cmp = function (other)  
    {  
        if(name<other.name)return -1;  
        if(name>other.name)return 1;  
        return 0;  
    }  
}  
  
local a=delegate comparable : { name="Alberto" };  
local b=delegate comparable : { name="Wouter" };
```

```
if(a>b)
    print("a>b")
else
    print("b<=a");
```

for classes the previous code become:

```
class Comparable {
    constructor(n)
    {
        name = n;
    }
    function _cmp(other)
    {
        if(name<other.name) return -1;
        if(name>other.name) return 1;
        return 0;
    }
    name = null;
}

local a = Comparable("Alberto");
local b = Comparable("Wouter");

if(a>b)
    print("a>b")
else
    print("b<=a");
```

## **\_set**

invoked when the index idx is not present in the object or in its delegate chain

```
function _set(idx,val) //returns val
```

## **\_get**

invoked when the index idx is not present in the object or in its delegate chain

```
function _get(idx) //return the fetched values
```

## **\_newslot**

invoked when a script tries to add a new slot in a table.

```
function _newslot(key,value) //returns val
```

if the slot already exists in the target table the method will not be invoked also if the “new slot” operator is used.

## **\_delslot**



invoked when a script deletes a slot from a table.

if the method is invoked squirrel will not try to delete the slot himself

```
function _delslot(key)
```

## **`_add`**

the + operator

```
function _add(op) //returns this+op
```

## **`_sub`**

the – operator (like `_add`)

## **`_mul`**

the \* operator (like `_add`)

## **`_div`**

the / operator (like `_add`)

## **`_modulo`**

the % operator (like `_add`)

## **`_unm`**

the unary minus operator

```
function _unm()
```

## **`_typeof`**

invoked by the `typeof` operator on tables ,userdata and class instances

```
function _typeof() //returns the type of this as string
```

## **`_cmp`**

invoked to emulate the < > <= >= operators

```
function _cmp(other)
```

returns an integer:

```
>0 | if this > other
```

---

0	if this == other
<0	if this < other

## **`__call`**

invoked when a table, userdata or class instance is called

```
function __call(original_this, params...)
```

## **`__cloned`**

invoked when a table or class instance is cloned(in the cloned table)

```
function __cloned(original)
```

## **`__nexti`**

invoked when a userdata or class instance is iterated by a foreach loop

```
function __nexti(previdx)
```

if previdx==null it means that it is the first iteration. The function has to return the index of the 'next' value.

## **`__tostring`**

invoked when during string concatenation or when the `print` function prints a table, instance or userdata. The method is also invoked by the `sq_tostring()` api

```
function __tostring()
```

must return a string representation of the object.

## **`__inherited`**

invoked when a class object inherits from the class implementing `__inherited` the `this` contains the new class.

```
function __inherited(attributes)
```

return value is ignored.

## **`__newmember`**

invoked for each member declared in a class body(at declaration time).

```
function __newmember(index, value, attributes)
```

if the function is implemented, members will not be added to the class.

# Built-in functions

The squirrel virtual machine has a set of built utility functions.

## Global symbols

`array(size,[fill])`  
create and returns array of a specified size. if the optional parameter *fill* is specified its value will be used to fill the new array's slots. If the *fill* paramter is omitted `null` is used instead.

`seterrorhandler(func)`  
sets the runtime error handler

`setdebughook(hook_func)`  
sets the debug hook

`enableddebuginfo(enable)`  
enable/disable the debug line information generation at compile time. `enable != null` enables . `enable == null` disables.

`getroottable()`  
returns the root table of the VM.

`setroottable(table)`  
sets the root table of the VM.

`getconsttable()`  
returns the const table of the VM.

`setconsttable(table)`  
sets the const table of the VM.

`assert(exp)`  
throws an exception if `exp` is null

`print(x)`  
prints `x` in the standard output

`compilestring(string,[buffername])`  
compiles a string containing a squirrel script into a function and returns it

```
local compiledscript=compilestring("::print(\"ciao\")");  
//run the script  
compiledscript();
```

`collectgarbage()`  
calls the garbage collector and returns the number of reference cycles found(and deleted)

`type(obj)`  
return the 'raw' type of an object without invoking the metatmethod `'_typeof'`.

`getstackinfos(level)`  
returns the stack informations of a given call stack level. returns a table formatted as follow:

```
{
    func="DoStuff", //function name
    src="test.nut", //source file
    line=10,        //line number
    locals = {      //a table containing the local variables
        a=10,
        testy="I'm a string"
    }
}
```

level = 0 is the current function, level = 1 is the caller and so on. If the stack level doesn't exist the function returns null.

`newthread(threadfunc)`  
creates a new cooperative thread object(coroutine) and returns it

`_version_`  
string values describing the version of VM and compiler.

`_charsize_`  
size in bytes of the internal VM representation for characters(1 for ASCII builds 2 for UNICODE builds).

`_intsize_`  
size in bytes of the internal VM representation for integers(4 for 32bits builds 8 for 64bits builds).

## Default delegates

Except null and userdata every squirrel object has a default delegate containing a set of functions to manipulate and retrieve information from the object itself.

## Integer

`tofloat()`  
convert the number to float and returns it

`tostring()`  
converts the number to string and returns it

`tointeger()`  
returns the value of the integer(dummy function)

`tochar()`  
returns a string containing a single character rapresented by the integer.

`weakref()`  
dummy function, returns the integer itself.

## Float

`tofloat()`  
returns the value of the float(dummy function)

`tointeger()`  
converts the number to integer and returns it

`tostring()`  
converts the number to string and returns it

`tochar()`  
returns a string containing a single character rapresented by the integer part of the float.

`weakref()`  
dummy function, returns the float itself.

## Bool

`tofloat()`  
returns 1.0 for true 0.0 for false

`tointeger()`  
returns 1 for true 0 for false

`tostring()`  
returns "true" for true "false" for false

`weakref()`  
dummy function, returns the bool itself.

## String

`len()`  
returns the string length

`tointeger()`  
converts the string to integer and returns it

`tofloat()`  
converts the string to float and returns it

`tostring()`  
returns the string(dummy function)

`slice(start,[end])`  
returns a section of the string as new string. Copies from start to the end (not included). If start is negative the index is calculated as length + start, if end is negative the index is calculated as length + start. If end is omitted end is equal to the string length.

`find(substr,[startidx])`  
search a sub string(substr) starting from the index startidx and returns the index of its first occurrence. If startidx is omitted the search operation starts from the beginning of the string. The function returns null if substr is not found.

`tolower()`  
returns a lowercase copy of the string.

`toupper()`  
returns an uppercase copy of the string.

`weakref()`  
returns a weak reference to the object.

## Table

`len()`  
returns the number of slots contained in a table

`rawget(key)`  
tries to get a value from the slot 'key' without employ delegation

`rawset(key,val)`  
sets the slot 'key' with the value 'val' without employing delegation. If the slot do not exists , it will be created.

`rawdelete()`  
deletes the slot key without employing delegetion and returnns his value. if the slo does not exists returns always null.

`rawin(key)`  
returns true if the slot 'key' exists. the function has the same eddect as the operator 'in' but does not employ delegation.

`weakref()`  
returns a weak reference to the object.

`tostring()`  
tries to invoke the `_tostring` metamethod, if failed. returns "(table : pointer)".

`clear()`  
removes all the slot from the table

## Array

`len()`  
returns the length of the array

`append(val)`  
appends the value 'val' at the end of the array

`push(val)`  
appends the value 'val' at the end of the array

`extend(array)`  
Extends the array by appending all the items in the given array.

`pop()`  
removes a value from the back of the array and returns it.

`top()`  
returns the value of the array with the higher index

`insert(idx, val)`  
inserst the value 'val' at the position 'idx' in the array

`remove(idx)`  
removes the value at the position 'idx' in the array

`resize(size, [fill])`  
resizes the array, if the optional parameter *fill* is specified its value will be used to fill the new array's slots(if the size specified is bigger than the previous size) . If the *fill* paramter is omitted null is used instead.

`sort([compare_func])`

sorts the array. a custom compare function can be optionally passed. The function prototype as to be the following.

```
function custom_compare(a,b)
{
    if(a>b) return 1
    else if(a<b) return -1
    return 0;
}
```

`reverse()`  
reverse the elements of the array in place

`slice(start,[end])`  
returns a section of the array as new array. Copies from start to the end (not included). If start is negative the index is calculated as length + start, if end is negative the index is calculated as length + start. If end is omitted end is equal to the array length.

`weakref()`  
returns a weak reference to the object.

`tostring()`  
returns the string "(array : pointer)".

`clear()`  
removes all the items from the array

## Function

`call(_this,args...)`  
calls the function with the specified environment object('this') and parameters

`pcall(_this,args...)`  
calls the function with the specified environment object('this') and parameters, this function will not invoke the error callback in case of failure(pcall stays for 'protected call')

`acall(array_args)`  
calls the function with the specified environment object('this') and parameters. The function accepts an array containing the parameters that will be passed to the called function.

`pacall(array_args)`  
calls the function with the specified environment object('this') and parameters. The function accepts an array containing the parameters that will be passed to the called function. This function will not invoke the error callback in case of failure(pacall stays for 'protected array call')

`weakref()`  
returns a weak reference to the object.



`tostring()`  
returns the string "(closure : pointer)".

`tostring()`  
returns the string "(closure : pointer)".

`bindenv(env)`  
clones the function(aka closure) and bind the enviroment object to it(table,class or instance). the `this` parameter of the newly create function will always be set to `env`. Note that the created function holds a weak reference to its environment object so cannot be used to control its lifetime.

## Class

`instance()`  
returns a new instance of the class. this function does not invoke the instance constructor. The constructor must be explicitly called( eg. `class_inst.constructor(class_inst)` ).

`getattributes(membername)`  
returns the attributes of the specified member. if the parameter member is null the function returns the class level attributes.

`getattributes(membername,attr)`  
sets the attribute of the specified member and returns the previous attribute value. if the parameter member is null the function sets the class level attributes.

`rawin(key)`  
returns true if the slot 'key' exists. the function has the same eddect as the operator 'in' but does not employ delegation.

`weakref()`  
returns a weak reference to the object.

`tostring()`  
returns the string "(class : pointer)".

## Class Instance

`getclass()`  
returns the class that created the instance.

`rawin(key)`  
returns true if the slot 'key' exists. the function has the same eddect as the operator 'in' but does not employ delegation.

`weakref()`  
returns a weak reference to the object.

`tostring()`  
tries to invoke the `_tostring` metamethod, if failed. returns "(insatnce : pointer)".

## Generator

`getstatus()`  
returns the status of the generator as string : "running", "dead" or "suspended".

`weakref()`  
returns a weak reference to the object.

`tostring()`  
returns the string "(generator : pointer)".

## Thread

`call(...)`  
starts the thread with the specified parameters

`wakeup([wakeupval])`  
wakes up a suspended thread, accepts a optional parameter that will be used as return value for the function that suspended the thread(usually `suspend()`)

`getstatus()`  
returns the status of the thread ("idle", "running", "suspended")

`weakref()`  
returns a weak reference to the object.

`tostring()`  
returns the string "(thread : pointer)".

## Weak Reference

`ref()`  
returns the object that the weak reference is pointing at, null if the object that was point at was destroyed.

`weakref()`  
returns a weak reference to the object.

`tostring()`  
returns the string "(weakref : pointer)".

---

# Chapter 3. Embedding Squirrel

*This section describes how to embed Squirrel in a host application, C language knowledge is required to understand this part of the manual.*

Because of his nature of extension language, Squirrel's compiler and virtual machine are implemented as C library. The library exposes a set of functions to compile scripts, call functions, manipulate data and extend the virtual machine. All declarations needed for embedding the language in an application are in the header file 'squirrel.h'.

## Memory management

Squirrel uses reference counting (RC) as primary system for memory management; however, the virtual machine (VM) has an auxiliary mark and sweep garbage collector that can be invoked on demand.

There are 2 possible compile time options:

- The default configuration consists in RC plus a mark and sweep garbage collector. The host program can call the function `sq_collectgarbage()` and perform a garbage collection cycle during the program execution. The garbage collector isn't invoked by the VM and has to be explicitly called by the host program.
- The second a situation consists in RC only(define `NO_GARBAGE_COLLECTOR`); in this case is impossible for the VM to detect reference cycles, so is the programmer that has to solve them explicitly in order to avoid memory leaks.

The only advantage introduced by the second option is that saves 2 additional pointers that have to be stored for each object in the default configuration with garbage collector(8 bytes for 32 bits systems). The types involved are: tables, arrays, functions, threads, userdata and generators; all other types are untouched. These options do not affect execution speed.

## Unicode

By default Squirrel strings are plain 8-bits ASCII characters; however if the symbol 'SQUNICODE' is defined the VM, compiler and API will use 16-bits characters.

## Squirrel on 64 bits architectures

Squirrel can be compiled on 64 bits architectures by defining '\_SQ64' in the C++ preprocessor. This flag should be defined in any project that includes 'squirrel.h'.

## Error conventions

Most of the functions in the API return a `SQRESULT` value; `SQRESULT` indicates if a function completed successfully or not. The macros `SQ_SUCCEEDED()` and `SQ_FAILED()` are used to test the result of a function.

```
if(SQ_FAILED(sq_getstring(v,-1,&s)))  
    printf("getstring failed");
```

## Initializing Squirrel

The first thing that a host application has to do, is create a virtual machine. The host application can create any number of virtual machines through the function `sq_open()`.

Every single VM has to be released with the function `sq_close()` when it is not needed anymore.

```
int main(int argc, char* argv[])
{
    HSQUIRRELVM v;
    v = sq_open(1024); //creates a VM with initial stack size 1024

    //do some stuff with squirrel here

    sq_close(v);
}
```

## The Stack

Squirrel exchanges values with the virtual machine through a stack. This mechanism has been inherited from the language Lua. For instance to call a Squirrel function from C it is necessary to push the function and the arguments in the stack and then invoke the function; also when Squirrel calls a C function the parameters will be in the stack as well.

## Stack indexes

Many API functions can arbitrarily refer to any element in the stack through an index. The stack indexes follow those conventions:

- 1 is the stack base
- Negative indexes are considered an offset from top of the stack. For instance -1 is the top of the stack.
- 0 is an invalid index

Here an example (let's pretend that this table is the VM stack)

<i>STACK</i>	<i>positive index</i>	<i>negative index</i>
"test "	4	-1(top)
1	3	-2
0.5	2	-3
"foo"	1(base)	-4

In this case, the function `sq_gettop` would return 4;

## Stack manipulation

The API offers several functions to push and retrieve data from the Squirrel stack.

To push a value that is already present in the stack in the top position

```
void sq_push(HSQIRRELVM v, SQInteger idx);
```

To pop an arbitrary number of elements

```
void sq_pop(HSQIRRELVM v, SQInteger nelemstopop);
```

To remove an element from the stack

```
void sq_remove(HSQIRRELVM v, SQInteger idx);
```

To retrieve the top index (and size) of the current virtual stack you must call `sq_gettop`

```
SQInteger sq_gettop(HSQIRRELVM v);
```

To force the stack to a certain size you can call `sq_settop`

```
void sq_settop(HSQIRRELVM v, SQInteger newtop);
```

If the newtop is bigger than the previous one, the new positions in the stack will be filled with null values.

The following function pushes a C value into the stack

```
void sq_pushstring(HSQIRRELVM v, const SQChar *s, SQInteger len);  
void sq_pushfloat(HSQIRRELVM v, SQFloat f);  
void sq_pushinteger(HSQIRRELVM v, SQInteger n);  
void sq_pushuserpointer(HSQIRRELVM v, SQUserPointer p);  
void sq_pushbool(HSQIRRELVM v, SQBool b);
```

this function pushes a null into the stack

```
void sq_pushnull(HSQIRRELVM v);
```

returns the type of the value in a arbitrary position in the stack

```
SQObjectType sq_gettype(HSQIRRELVM v, SQInteger idx);
```

the result can be one of the following values:

```
OT_NULL, OT_INTEGER, OT_FLOAT, OT_STRING, OT_TABLE, OT_ARRAY, OT_USERDATA,  
OT_CLOSURE, OT_NATIVECLOSURE, OT_GENERATOR, OT_USERPOINTER, OT_BOOL, OT_INSTANCE, OT_CLA
```

The following functions convert a squirrel value in the stack to a C value

```
SQRESULT sq_getstring(HSQIRRELVM v, SQInteger idx, const SQChar **c);
SQRESULT sq_getinteger(HSQIRRELVM v, SQInteger idx, SQInteger *i);
SQRESULT sq_getfloat(HSQIRRELVM v, SQInteger idx, SQFloat *f);
SQRESULT sq_getuserpointer(HSQIRRELVM v, SQInteger idx, SQUserPointer *p);
SQRESULT sq_getuserdata(HSQIRRELVM v, SQInteger idx, SQUserPointer *p, SQUserPointer *p2);
SQRESULT sq_getbool(HSQIRRELVM v, SQInteger idx, SQBool *b);
```

The function `sq_cmp` compares 2 values from the stack and returns their relation (like `strcmp()` in ANSI C).

```
SQInteger sq_cmp(HSQIRRELVM v);
```

## Runtime error handling

When an exception is not handled by Squirrel code with a try/catch statement, a runtime error is raised and the execution of the current program is interrupted. It is possible to set a call back function to intercept the runtime error from the host program; this is useful to show meaningful errors to the script writer and for implementing visual debuggers. The following API call pops a Squirrel function from the stack and sets it as error handler.

```
SQUIRREL_API void sq_seterrorhandler(HSQIRRELVM v);
```

The error handler is called with 2 parameters, an environment object (this) and a object. The object can be any squirrel type.

## Compiling a script

You can compile a Squirrel script with the function `sq_compile`.

```
typedef SQInteger (*SQLEXREADFUNC)(SQUserPointer userdata);

SQRESULT sq_compile(HSQIRRELVM v, SQREADFUNC read, SQUserPointer p,
    const SQChar *sourcename, SQBool raiseerror);
```

In order to compile a script is necessary for the host application to implement a reader function (`SQLEXREADFUNC`); this function is used to feed the compiler with the script data. The function is called every time the compiler needs a character; It has to return a character code if succeed or 0 if the source is finished.

If `sq_compile` succeeds, the compiled script will be pushed as Squirrel function in the stack.

### Note

In order to execute the script, the function generated by `sq_compile()` has to be called through `sq_call()`

Here an example of a 'read' function that read from a file:

```
SQInteger file_lexfeedASCII(SQUserPointer file)
{
    int ret;
```

```

    char c;
    if( ( ret=fread(&c,sizeof(c),1,(FILE *)file )>0) )
        return c;
    return 0;
}

int compile_file(HSQUIRRELVm v,const char *filename)
{
    FILE *f=fopen(filename,"rb");
    if(f)
    {
        sq_compile(v,file_lexfeedASCII,file,filename,1);
        fclose(f);
        return 1;
    }
    return 0;
}

```

When the compiler fails for a syntax error it will try to call the ‘compiler error handler’; this function is must be declared as follow

```

typedef void (*SQCOMPILERERROR)(HSQUIRRELVm /*v*/,const SQChar * /*desc*/,const SQ
/*source*/,SQInteger /*line*/,SQInteger /*column*/);

```

and can be set with the following API call

```

void sq_setcompilererrorhandler(HSQUIRRELVm v,SQCOMPILERERROR f);

```

## Calling a function

To call a squirrel function it is necessary to push the function in the stack followed by the parameters and then call the function `sq_call`. The function will pop the parameters and push the return value if the last `sq_call` parameter is `>0`.

```

sq_pushroottable(v);
sq_pushstring(v,"foo",-1);
sq_get(v,-2); //get the function from the root table
sq_pushroottable(v); //‘this’ (function environment object)
sq_pushinteger(v,1);
sq_pushfloat(v,2.0);
sq_pushstring(v,"three",-1);
sq_call(v,4,SQFalse);
sq_pop(v,2); //pops the roottable and the function

```

this is equivalent to the following Squirrel code

```

foo(1,2.0,"three");

```

If a runtime error occurs (or a exception is thrown) during the squirrel code execution the `sq_call` will fail.

## Create a C function

A native C function must have the following prototype:

```
typedef SQInteger (*SQFUNCTION)(HSQUIRRELVm);
```

The parameters is an handle to the calling VM and the return value is an integer respecting the following rules:

- 1 if the function returns a value
- 0 if the function does not return a value
- `SQ_ERROR` runtime error is thrown

In order to obtain a new callable squirrel function from a C function pointer, is necessary to call `sq_newclosure()` passing the C function to it; the new Squirrel function will be pushed in the stack.

When the function is called, the stackbase is the first parameter of the function and the top is the last. In order to return a value the function has to push it in the stack and return 1.

Function parameters are in the stack from position 1 ('this') to n. `sq_gettop()` can be used to determine the number of parameters.

If the function has free variables, those will be in the stack after the explicit parameters and can be handled as normal parameters. Note also that the value returned by `sq_gettop()` will be affected by free variables. `sq_gettop()` will return the number of parameters plus number of free variables.

Here an example, the following function print the value of each argument and return the number of arguments.

```
SQInteger print_args(HSQUIRRELVm v)
{
    SQInteger nargs = sq_gettop(v); //number of arguments
    for(SQInteger n=1;n<=nargs;n++)
    {
        printf("arg %d is ",n);
        switch(sq_gettype(v,n))
        {
            case OT_NULL:
                printf("null");
                break;
            case OT_INTEGER:
                printf("integer");
                break;
            case OT_FLOAT:
                printf("float");
                break;
            case OT_STRING:
                printf("string");
                break;
            case OT_TABLE:
                printf("table");
                break;
            case OT_ARRAY:
                printf("array");
                break;
        }
    }
}
```



```

        break;
    case OT_USERDATA:
        printf("userdata");
        break;
    case OT_CLOSURE:
        printf("closure(function)");
        break;
    case OT_NATIVECLOSURE:
        printf("native closure(C function)");
        break;
    case OT_GENERATOR:
        printf("generator");
        break;
    case OT_USERPOINTER:
        printf("userpointer");
        break;
    case OT_CLASS:
        printf("class");
        break;
    case OT_INSTANCE:
        printf("instance");
        break;
    case OT_WEAKREF:
        printf("weak reference");
        break;
    default:
        return sq_throwerror(v,"invalid param"); //throws an exception
    }
}
printf("\n");
sq_pushinteger(v,nargs); //push the number of arguments as return value
return 1; //1 because 1 value is returned
}

```

Here an example of how to register a function

```

SQInteger register_global_func(HSQIRRELVM v,SQFUNCTION f,const char *fname)
{
    sq_pushroottable(v);
    sq_pushstring(v,fname,-1);
    sq_newclosure(v,f,0,0); //create a new function
    sq_createslot(v,-3);
    sq_pop(v,1); //pops the root table
}

```

## Tables and arrays manipulation

A new table is created calling `sq_newtable`, this function pushes a new table in the stack.

```
void sq_newtable (HSQIRRELVM v);
```

To create a new slot

```
SQRESULT sq_createslot(HSQIRRELVM v,SQInteger idx);
```

To set or get the table delegate

```
SQRESULT sq_setdelegate(HSQIRRELVM v,SQInteger idx);
SQRESULT sq_getdelegate(HSQIRRELVM v,SQInteger idx);
```

A new array is created calling `sq_newarray`, the function pushes a new array in the stack; if the parameters size is bigger than 0 the elements are initialized to null.

```
void sq_newarray (HSQIRRELVM v,SQInteger size);
```

To append a value to the back of the array

```
SQRESULT sq_arrayappend(HSQIRRELVM v,SQInteger idx);
```

To remove a value from the back of the array

```
SQRESULT sq_arraypop(HSQIRRELVM v,SQInteger idx,SQInteger pushval);
```

To resize the array

```
SQRESULT sq_arrayresize(HSQIRRELVM v,SQInteger idx,SQInteger newsize);
```

To retrieve the size of a table or an array you must use `sq_getsize()`

```
SQInteger sq_getsize(HSQIRRELVM v,SQInteger idx);
```

To set a value in an array or table

```
SQRESULT sq_set(HSQIRRELVM v,SQInteger idx);
```

To get a value from an array or table

```
SQRESULT sq_get(HSQIRRELVM v,SQInteger idx);
```

To get or set a value from a table without employ delegation

```
SQRESULT sq_rawget(HSQIRRELVM v,SQInteger idx);
SQRESULT sq_rawset(HSQIRRELVM v,SQInteger idx);
```

To iterate a table or an array

```
SQRESULT sq_next(HSQIRRELVM v,SQInteger idx);
```

Here an example of how to perform an iteration:

```
//push your table/array here
sq_pushnull(v) //null iterator
```

```
while(SQ_SUCCEEDED(sq_next(v,-2)))
{
    //here -1 is the value and -2 is the key

    sq_pop(v,2); //pops key and val before the nex iteration
}

sq_pop(v,1); //pops the null iterator
```

## Userdata and UserPointers

Squirrel allows the host application put arbitrary data chunks into a Squirrel value, this is possible through the data type userdata.

```
SQUserPointer sq_newuserdata (HSQUIRRELVM v,SQUnsignedInteger size);
```

When the function `sq_newuserdata` is called, Squirrel allocates a new userdata with the specified size, returns a pointer to his payload buffer and push the object in the stack; at this point the application can do whatever it want with this memory chunk, the VM will automatically take care of the memory deallocation like for every other built-in type. A userdata can be passed to a function or stored in a table slot. By default Squirrel cannot manipulate directly userdata; however is possible to assign a delegate to it and define a behavior like it would be a table. Because the application would want to do something with the data stored in a userdata object when it get deleted, is possible to assign a callback that will be called by the VM just before deleting a certain userdata. This is done through the API call `sq_setreleasehook`.

```
typedef SQInteger (*SQRELEASEHOOK)(SQUserPointer,SQInteger size);

void sq_setreleasehook(HSQUIRRELVM v,SQInteger idx,SQRELEASEHOOK hook);
```

Another kind of userdata is the userpointer; this type is not a memory chunk like the normal userdata, but just a 'void\*' pointer. It cannot have a delegate and is passed by value, so pushing a userpointer doesn't cause any memory allocation.

```
void sq_pushuserpointer(HSQUIRRELVM v,SQUserPointer p);
```

## The registry table

The registry table is an hidden table shared between vm and all his thread(friend vms). This table is accessible only through the C API and is ment to be an utility structure for native C library implementation. For instance the `sqstdlib`(squirrel standard library)uses it to store configuration and shared objects delegates. The registry is accessible through the API call `sq_pushregistrytable`.

```
void sq_pushregistrytable(HSQUIRRELVM v);
```

## Mantaining strong references to Squirrel values from the C API

Squirrel allows to reference values through the C API; the function `sq_getstackobject()` gets a handle to a squirrel object(any type). The object handle can be used to control the lifetime of an object by adding or removing references to it( see `sq_addref()` and `sq_release()`). The object can be also re-pushed in the VM stack using `sq_pushobject()`.

```
HSQOBJECT obj;

sq_resetobject(v,&obj) //initialize the handle
sq_getstackobject(v,-2,&obj); //retrieve an object handle from the pos -2
sq_addref(v,&obj); //adds a reference to the object

... //do stuff

sq_pushobject(v,&obj); //push the object in the stack
sq_release(v,&obj); //release the object
```

## Debug Interface

The squirrel VM exposes a very simple debug interface that allows to easily built a full featured debugger. Through the function `sq_setdebughook` is possible in fact to set a callback function that will be called every time the VM executes an new line of a script or if a function get called/returns. The callback will pass as argument the current line the current source and the current function name (if any).

```
SQUIRREL_API void sq_setdebughook(HSQUIRRELVm v);
```

The following code shows how a debug hook could look like(Obviously is possible to implement this function in C as well).

```
function debughook(event_type,sourcefile,line,funcname)
{
    local fname=funcname?funcname:"unknown";
    local srcfile=sourcefile?sourcefile:"unknown"
    switch (event_type) {
        case 'l': //called every line(that contains some code)
            ::print("LINE line [" + line + "] func [" + fname + "]");
            ::print("file [" + srcfile + "]\n");
            break;
        case 'c': //called when a function has been called
            ::print("LINE line [" + line + "] func [" + fname + "]");
            ::print("file [" + srcfile + "]\n");
            break;
        case 'r': //called when a function returns
            ::print("LINE line [" + line + "] func [" + fname + "]");
            ::print("file [" + srcfile + "]\n");
            break;
    }
}
```

The parameter `event_type` can be 'l','c' or 'r'; a hook with a 'l' event is called for each line that gets executed, 'c' every time a function gets called and 'r' every time a function returns.

A full-featured debugger always allows displaying local variables and calls stack. The call stack information are retrieved through `sq_getstackinfos()`

```
SQInteger sq_stackinfos(HSQUIRRELVm v, SQInteger level, SQStackInfos *si);
```

While the local variables info through `sq_getlocal()`

```
SQInteger sq_getlocal(HSQUIRRELVm v, SQUnsignedInteger level, SQUnsignedInteger nseq
```

In order to receive line callbacks the scripts have to be compiled with debug infos enabled this is done through `sq_enableddebuginfo()`;

```
void sq_enableddebuginfo(HSQUIRRELVm v, SQInteger debuginfo);
```

---

# Chapter 4. API Reference

## Virtual Machine

sq\_close

```
void sq_close(HSQUIRRELVM v);
```

release a squirrel VM and all related friend VMs

parameters:

*HSQUIRRELVM v* the target VM

sq\_getforeignptr

```
SQUserPointer sq_getforeignptr(HSQUIRRELVM v);
```

Returns the foreign pointer of a VM instance.

parameters:

*HSQUIRRELVM v* the target VM

return: the current VMs foreign pointer.

sq\_getprintfunc

```
SQPRINTFUNCTION sq_getprintfunc(HSQUIRRELVM v);
```

returns the current print function of the given Virtual machine. (see sq\_setprintfunc())

parameters:

*HSQUIRRELVM v* the target VM

return: a pointer to a SQPRINTFUNCTION, or NULL if no function has been set.

sq\_getvmstate

```
SQInteger sq_getvmstate(HSQUIRRELVM v);
```

returns the execution state of a virtual machine

parameters:

*HSQUIRRELVM v* the target VM

return: the state of the vm encoded as integer value. The following constants are defined:  
SQ\_VMSTATE\_IDLE, SQ\_VMSTATE\_RUNNING,  
SQ\_VMSTATE\_SUSPENDED.

<code>sq_move</code>
----------------------

```
void sq_move(HSQUIRRELVM dest, HSQUIRRELVM src, SQInteger idx);
```

pushes the object at the position 'idx' of the source vm stack in the destination vm stack.

parameters:

*HSQUIRRELVM dest* the destination VM

*HSQUIRRELVM src* the source VM

*SQInteger idx* the index in the source stack of the value that has to be moved

<code>sq_newthread</code>
---------------------------

```
HSQUIRRELVM sq_newthread(HSQUIRRELVM friendvm, SQInteger initialstacksize);
```

creates a new vm friendvm of the one passed as first parameter and pushes it in its stack as "thread" object.

parameters:

*HSQUIRRELVM friendvm* a friend VM

*SQInteger initialstacksize* the size of the stack in slots(number of objects)

return: a pointer to the new VM.

remarks: By default the roottable is shared with the VM passed as first parameter. The new VM lifetime is bound to the "thread" object pushed in the stack and behave like a normal squirrel object.

<code>sq_open</code>
----------------------

```
HSQUIRRELVM sq_open(SQInteger initialstacksize);
```

creates a new instance of a squirrel VM that consists in a new execution stack.

parameters:

*SQInteger initialstacksize* the size of the stack in slots(number of objects)

return: an handle to a squirrel vm

remarks: the returned VM has to be released with `sq_releasevm`

`sq_pushconsttable`

```
SQRESULT sq_pushconsttable(HSQUIRRELVM v);
```

pushes the current const table in the stack

parameters:

*HSQUIRRELVM v* the target VM

`sq_pushregistrytable`

```
SQRESULT sq_pushregistrytable(HSQUIRRELVM v);
```

pushes the registry table in the stack

parameters:

*HSQUIRRELVM v* the target VM

`sq_pushroottable`

```
SQRESULT sq_pushroottable(HSQUIRRELVM v);
```

pushes the current root table in the stack

parameters:

*HSQUIRRELVM v* the target VM

`sq_setconsttable`

```
void sq_setconsttable(HSQUIRRELVM v);
```

pops a table from the stack and set it as const table



parameters:

*HSQUIRRELM v* the target VM

`sq_seterrorhandler`

```
void sq_seterrorhandler(HSQUIRRELM v);
```

pops from the stack a closure or native closure and sets it as runtime-error handler.

parameters:

*HSQUIRRELM v* the target VM

remarks: the error handler is shared by friend VMs

`sq_setforeignptr`

```
void sq_setforeignptr(HSQUIRRELM v, SQUserPointer p);
```

Sets the foreign pointer of a certain VM instance. The foreign pointer is an arbitrary user defined pointer associated to a VM (by default is value id 0). This pointer is ignored by the VM.

parameters:

*HSQUIRRELM v* the target VM

*SQUserPointer p* The pointer that has to be set

`sq_setprintfunc`

```
void sq_setprintfunc(HSQUIRRELM v, SQPRINTFUNCTION printfunc);
```

sets the print function of the virtual machine. This function is used by the built-in function '::print()' to output text.

parameters:

*HSQUIRRELM v* the target VM

*SQPRINTFUNCTION printfunc* a pointer to the print func or NULL to disable the output.

remarks: the print func has the following prototype: void printfunc(HSQUIRRELM v, const SQChar \*s,...)

sq\_setroottable

```
void sq_setroottable(HSQUIRRELVM v);
```

pops a table from the stack and set it as root table

parameters:

*HSQUIRRELVM v*    the target VM

sq\_suspendvm

```
HRESULT sq_suspendvm(HSQUIRRELVM v);
```

Suspends the execution of the specified vm.

parameters:

*HSQUIRRELVM v*    the target VM

return:            an SQRRESULT(that has to be returned by a C function)

remarks:           *sq\_result* can only be called as return expression of a C function. The function will fail if the suspension is done through more C calls or in a metamethod.

eg.

```
SQInteger suspend_vm_example(HSQUIRRELVM v)
{
    return sq_suspendvm(v);
}
```

sq\_wakeupvm

```
HRESULT sq_wakeupvm(HSQUIRRELVM v, SQBool resumedret, SQBool retval,
SQBool raiseerror);
```

Wake up the execution a previously suspended virtual machine.

parameters:

*HSQUIRRELVM v*            the target VM

*SQBool resumedret*    if true the function will pop a value from the stack and use it as return value for the function that has previously suspended the virtual machine.

*SQBool retval*            if true the function will push the return value of the func-

tion that suspend the excution or the main function one.

*SQBool raiseerror* if true, if a runtime error occurs during the execution of the call, the vm will invoke the error handler.

return: an HRESULT.

## Compiler

`sq_compile`

```
SQRESULT sq_compile(HSQUIRRELVm v, HSQLEXREADFUNC read, SQUserPointer p, const SQChar * sourcename, SQBool raiseerror);
```

compiles a squirrel program; if it succeeds, push the compiled script as function in the stack.

parameters:

<i>HSQUIRRELVm v</i>	the target VM
<i>HSQLEXREADFUNC read</i>	a pointer to a read function that will feed the compiler with the program.
<i>SQUserPointer p</i>	a user defined pointer that will be passed by the compiler to the read function at each invocation.
<i>const SQChar * sourcename</i>	the symbolic name of the program (used only for more meaningful runtime errors)
<i>SQBool raiseerror</i>	if this value is true the compiler error handler will be called in case of an error

return: a SQRESULT. If the `sq_compile` fails nothing is pushed in the stack.

remarks: in case of an error the function will call the function set by `sq_setcompilererrorhandler()`.

`sq_compilebuffer`

```
SQRESULT sq_compilebuffer(HSQUIRRELVm v, const SQChar* s, SQInteger size, const SQChar * sourcename, SQBool raiseerror);
```

compiles a squirrel program from a memory buffer; if it succeeds, push the compiled script as function in the stack.

parameters:

<i>HSQUIRRELVm v</i>	the target VM
----------------------	---------------

<i>const SQChar* s</i>	a pointer to the buffer that has to be compiled.
<i>SQInteger size</i>	size in characters of the buffer passed in the parameter 's'.
<i>const SQChar * sourcename</i>	the symbolic name of the program (used only for more meaningful runtime errors)
<i>SQBool raiseerror</i>	if this value true the compiler error handler will be called in case of an error

return: a SQRESULT. If the sq\_compilebuffer fails nothing is pushed in the stack.

remarks: in case of an error the function will call the function set by sq\_setcompilererrorhandler().

`sq_enableddebuginfo`

```
void sq_enableddebuginfo(HSQUIRRELVM v, SQBool enable);
```

enable/disable the debug line information generation at compile time.

parameters:

*HSQUIRRELVM v* the target VM

*SQBool enable* if true enables the debug info generation, if == 0 disables it.

remarks: The function affects all threads as well.

`sq_notifyallexceptions`

```
void sq_notifyallexceptions(HSQUIRRELVM v, SQBool enable);
```

enable/disable the error callback notification of handled exceptions.

parameters:

*HSQUIRRELVM v* the target VM

*SQBool enable* if true enables the error callback notification of handled exceptions.

remarks: By default the VM will invoke the error callback only if an exception is not handled (no try/catch traps are present in the call stack). If notifyallexceptions is enabled, the VM will call the error callback for any exception even if between try/catch blocks. This feature is useful for implementing debuggers.

`sq_setcompilererrorhandler`

```
void sq_setcompilererrorhandler(HSQUIRRELVM v, SQCOMPILERERROR f);
```

sets the compiler error handler function

parameters:

*HSQUIRRELVM v*            the target VM

*SQCOMPILERERROR f*    A pointer to the error handler function

remarks:            if the parameter f is NULL no function will be called when a compiler error occurs.  
The compiler error handler is shared between friend VMs.

## Stack Operations

`sq_cmp`

```
SQInteger sq_cmp(HSQUIRRELVM v);
```

compares 2 object from the stack and compares them.

parameters:

*HSQUIRRELVM v*    the target VM

return:            > 0 if obj1>obj2  
                  == 0 if obj1==obj2  
                  < 0 if obj1<obj2

`sq_gettop`

```
SQInteger sq_gettop(HSQUIRRELVM v);
```

returns the index of the top of the stack

parameters:

*HSQUIRRELVM v*    the target VM

return:            an integer representing the index of the top of the stack

`sq_pop`

```
void sq_pop(HSQUIRRELVM v, SQInteger nelementstopop);
```

pops *n* elements from the stack

parameters:

*HSQUIRRELVM v*                      the target VM  
*SQInteger nelementstopop*   the number of elements to pop

sq\_poptop

```
void sq_poptop(HSQUIRRELVM v);
```

pops 1 object from the stack

parameters:

*HSQUIRRELVM v*   the target VM

sq\_push

```
void sq_push(HSQUIRRELVM v, SQInteger idx);
```

pushes in the stack the value at the index *idx*

parameters:

*HSQUIRRELVM v*   the target VM  
*SQInteger idx*   the index in the stack of the value that has to be pushed

sq\_remove

```
void sq_remove(HSQUIRRELVM v, SQInteger idx);
```

removes an element from an arbitrary position in the stack

parameters:

*HSQUIRRELVM v*   the target VM  
*SQInteger idx*   index of the element that has to be removed

sq\_reservestack

```
void sq_reservestack(HSQUIRRELVM v, SQInteger nsize);
```

ensure that the stack space left is at least of a specified size.If the stack is smaller it will automatically grow.

parameters:

*HSQUIRRELVM v*      the target VM  
*SQInteger nsize*    required stack size

`sq_settop`

```
void sq_settop(HSQUIRRELVM v, SQInteger v);
```

resize the stack, if new top is bigger then the current top the function will push nulls.

parameters:

*HSQUIRRELVM v*    the target VM  
*SQInteger v*       the new top index

## Object creation and handling

`sq_bindenv`

```
SQRESULT sq_bindenv(HSQUIRRELVM v, SQInteger idx);
```

pops an object from the stack(must be a table,instance or class) clones the closure at position idx in the stack and sets the popped object as environment of the cloned closure. Then pushes the new cloned closure on top of the stack.

parameters:

*HSQUIRRELVM v*    the target VM  
*SQInteger idx*    index of the target closure

return:            a SQRESULT

remarks:           the cloned closure holds the environment object as weak reference

`sq_createinstance`

```
SQRESULT sq_createinstance(HSQUIRRELVM v, SQInteger idx);
```

creates an instance of the class at 'idx' position in the stack. The new class instance is pushed on top of

the stack.

parameters:

*HSQUIRRELVM v*    the target VM  
*SQInteger idx*    index of the target class

return:            a SQRESULT

remarks:           the function doesn't invoke the instance constructor. To create an instance and automatically invoke its constructor, `sq_call` must be used instead.

`sq_getbool`

SQRESULT **sq\_getbool**(HSQUIRRELVM v, SQInteger idx, SQBool \* b);

gets the value of the bool at the idx position in the stack.

parameters:

*HSQUIRRELVM v*    the target VM  
*SQInteger idx*    an index in the stack  
*SQBool \* b*        A pointer to the bool that will store the value

return:            a SQRESULT

`sq_getclosureinfo`

SQRESULT **sq\_getclosureinfo**(HSQUIRRELVM v, SQInteger idx, SQUnsignedInteger \* nparams, SQUnsignedInteger \* nfreevars);

retrieves number of parameters and number of freevariables from a squirrel closure.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	index of the target closure
<i>SQUnsignedInteger * nparams</i>	a pointer to an unsigned integer that will store the number of parameters
<i>SQUnsignedInteger * nfreevars</i>	a pointer to an unsigned integer that will store the number of free variables

return:            an SQRESULT



sq\_getfloat

```
SQRESULT sq_getfloat(HSQUIRRELVM v, SQInteger idx, SQFloat * f);
```

gets the value of the float at the idx position in the stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	an index in the stack
<i>SQFloat * f</i>	A pointer to the float that will store the value

return: a SQRESULT

sq\_getinstanceup

```
SQRESULT sq_getinstanceup(HSQUIRRELVM v, SQInteger idx, SQUserPointer * up, SQUserPointer typetag);
```

gets the userpointer of the class instance at position idx in the stack. if the parameter 'typetag' is different than 0, the function checks that the class or a base class of the instance is tagged with the specified tag; if not the function fails. If 'typetag' is 0 the function will ignore the tag check.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	an index in the stack
<i>SQUserPointer * up</i>	a pointer to the userpointer that will store the result
<i>SQUserPointer typetag</i>	the typetag that has to be checked, if this value is set to 0 the typetag is ignored.

return: a SQRESULT

sq\_getinteger

```
SQRESULT sq_getinteger(HSQUIRRELVM v, SQInteger idx, SQInteger * i);
```

gets the value of the integer at the idx position in the stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	an index in the stack

*SQInteger* \* *i*    A pointer to the integer that will store the value

return:            a SQRESULT

`sq_getscratchpad`

SQChar \* **sq\_getscratchpad**(HSQUIRRELVM *v*, SQInteger *minsize*);

returns a pointer to a memory buffer that is at least as big as *minsize*.

parameters:

*HSQUIRRELVM v*            the target VM

*SQInteger minsize*    the requested size for the scratchpad buffer

remarks:            the buffer is valid until the next call to `sq_getscratchpad`

`sq_getsize`

SQObjectType **sq\_getsize**(HSQUIRRELVM *v*, SQInteger *idx*);

returns the size of a value at the *idx* position in the stack

parameters:

*HSQUIRRELVM v*    the target VM

*SQInteger idx*    an index in the stack

return:            the size of the value at the position *idx* in the stack

remarks:            this function only works with strings, arrays, tables and userdata if the value is not one of those types the function will return -1

`sq_getstring`

SQRESULT **sq\_getstring**(HSQUIRRELVM *v*, SQInteger *idx*, const SQChar \*\* *c*);

gets a pointer to the string at the *idx* position in the stack.

parameters:

*HSQUIRRELVM v*            the target VM

*SQInteger idx*            an index in the stack

*const SQChar \*\* c* a pointer to the pointer that will point to the string

return: a SQRESULT

`sq_getthread`

SQRESULT **sq\_getthread**(HSQUIRRELVM *v*, SQInteger *idx*, HSQUIRRELVM\* *v*);

gets a pointer to the thread the *idx* position in the stack.

parameters:

*HSQUIRRELVM v* the target VM

*SQInteger idx* an index in the stack

*HSQUIRRELVM\* v* A pointer to the variable that will store the thread pointer

return: a SQRESULT

`sq_gettype`

SQObjectType **sq\_gettype**(HSQUIRRELVM *v*, SQInteger *idx*);

the type of the value at the position *idx* in the stack

parameters:

*HSQUIRRELVM v* the target VM

*SQInteger idx* an index in the stack

return: the type of the value at the position *idx* in the stack

`sq_gettypetag`

SQRESULT **sq\_gettypetag**(HSQUIRRELVM *v*, SQInteger *idx*, SQUserPointer\* *typetag*);

gets the typetag of the object(userdata or class) at position *idx* in the stack.

parameters:

*HSQUIRRELVM v* the target VM

*SQInteger idx* an index in the stack

*SQUserPointer \* typetag* a pointer to the variable that will store the tag

return: a SQRESULT

remarks: the function works also with instances. if the target object is an instance, the typetag of it's base class is fetched.

`sq_getuserdata`

SQRESULT **sq\_getuserdata**(HSQUIRRELVM v, SQInteger idx, SQUserPointer \* p, SQUserPointer \* typetag);

gets a pointer to the value of the userdata at the idx position in the stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	an index in the stack
<i>SQUserPointer * p</i>	A pointer to the userpointer that will point to the userdata's payload
<i>SQUserPointer * typetag</i>	A pointer to a SQUserPointer that will store the userdata tag(see sq_settypetag). The parameter can be NULL.

return: a SQRESULT

`sq_getuserpointer`

SQRESULT **sq\_getuserpointer**(HSQUIRRELVM v, SQInteger idx, SQUserPointer \* p);

gets the value of the userpointer at the idx position in the stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	an index in the stack
<i>SQUserPointer * p</i>	A pointer to the userpointer that will store the value

return: a SQRESULT

`sq_newarray`

```
void sq_newarray(HSQUIRRELM v, SQInteger size);
```

creates a new array and pushes it in the stack

parameters:

<i>HSQUIRRELM v</i>	the target VM
<i>SQInteger size</i>	the size of the array that as to be created

`sq_newclass`

```
SQRESULT sq_newclass(HSQUIRRELM v, SQBool hasbase);
```

creates a new class object. If the parameter 'hasbase' is different than 0, the function pops a class from the stack and inherits the new created class from it.

parameters:

<i>HSQUIRRELM v</i>	the target VM
<i>SQBool hasbase</i>	if the parameter is true the function expects a base class on top of the stack.

return: a SQRESULT

`sq_newclosure`

```
void sq_newclosure(HSQUIRRELM v, HSQFUNCTION func, SQInteger nfreevars);
```

create a new native closure, pops n values set those as free variables of the new closure, and push the new closure in the stack.

parameters:

<i>HSQUIRRELM v</i>	the target VM
<i>HSQFUNCTION func</i>	a pointer to a native-function
<i>SQInteger nfreevars</i>	number of free variables(can be 0)

`sq_newtable`

```
void sq_newtable(HSQUIRRELM v);
```

creates a new table and pushes it in the stack

parameters:

*HSQUIRRELVM v* the target VM

`sq_newuserdata`

SQUserPointer **sq\_newuserdata**(HSQUIRRELVM v, SQUnsignedInteger size);

creates a new userdata and pushes it in the stack

parameters:

*HSQUIRRELVM v* the target VM

*SQUnsignedInteger size* the size of the userdata that as to be created in bytes

`sq_pushbool`

void **sq\_pushbool**(HSQUIRRELVM v, SQBool b);

pushes a bool into the stack

parameters:

*HSQUIRRELVM v* the target VM

*SQBool b* the bool that has to be pushed(SQTrue or SQFalse)

`sq_pushfloat`

void **sq\_pushfloat**(HSQUIRRELVM v, SQFloat f);

pushes a float into the stack

parameters:

*HSQUIRRELVM v* the target VM

*SQFloat f* the float that has to be pushed

`sq_pushinteger`

void **sq\_pushinteger**(HSQUIRRELVM v, SQInteger n);

pushes a integer into the stack

parameters:

*HSQUIRRELVM v*    the target VM  
*SQInteger n*       the integer that has to be pushed

<code>sq_pushnull</code>
--------------------------

void **sq\_pushnull**(HSQUIRRELVM v);

pushes a null value into the stack

parameters:

*HSQUIRRELVM v*    the target VM

<code>sq_pushstring</code>
----------------------------

void **sq\_pushstring**(HSQUIRRELVM v, const SQChar \* s, SQInteger len);

pushes a string in the stack

parameters:

*HSQUIRRELVM v*       the target VM  
*const SQChar \* s*    pointer to the string that has to be pushed  
*SQInteger len*       lenght of the string pointed by s

remarks:            if the parameter len is less than 0 the VM will calculate the length using strlen(s)

<code>sq_pushuserpointer</code>
---------------------------------

void **sq\_pushuserpointer**(HSQUIRRELVM v, SQUserPointer p);

pushes a userpointer into the stack

parameters:

*HSQUIRRELVM v*       the target VM  
*SQUserPointer p*    the pointer that as to be pushed

`sq_setclassudsize`

```
SQRESULT sq_setclassudsize(HSQUIRRELVM v, SQInteger idx, SQInteger udsiz);
```

Sets the user data size of a class. If a class 'user data size' is greater than 0. When an instance of the class is created additional space will be reserved at the end of the memory chunk where the instance is stored. The userpointer of the instance will also be automatically set to this memory area. This allows to minimize allocations in applications that have to carry data along with the class instance.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	an index in the stack pointing to the class
<i>SQInteger udsiz</i>	size in bytes reserved for user data

return: a SQRESULT

`sq_setinstanceup`

```
SQRESULT sq_setinstanceup(HSQUIRRELVM v, SQInteger idx, SQUserPointer up);
```

sets the userpointer of the class instance at position idx in the stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	an index in the stack
<i>SQUserPointer up</i>	an arbitrary user pointer

return: a SQRESULT

`sq_setnativeclosurename`

```
SQRESULT sq_setnativeclosurename(HSQUIRRELVM v, SQInteger idx, const SQChar * name);
```

sets the name of the native closure at the position idx in the stack. the name of a native closure is purely for debug purposes. The name is retrieved through the function `sq_stackinfos()` while the closure is in the call stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
----------------------	---------------



*SQInteger* *idx*                    index of the target native closure

*const SQChar \* name*    the name that has to be set

return:                    an SQRESULT

sq\_setparamscheck

```
SQRESULT sq_setparamscheck(HSQUIRRELM v, SQInteger nparamscheck,
const SQChar * typemask);
```

Sets the parameters validation scheme for the native closure at the top position in the stack. Allows to validate the number of parameters accepted by the function and optionally their types. If the function call does not comply with the parameter schema set by sq\_setparamscheck, an exception is thrown.

parameters:

<i>HSQUIRRELM v</i>	the target VM
<i>SQInteger nparamscheck</i>	defines the parameters number check policy(0 disable the param checking). if nparamscheck is greater than 0 the VM ensures that the number of parameters is exactly the number specified in nparamscheck(eg. if nparamscheck == 3 the function can only be called with 3 parameters). if nparamscheck is less than 0 the VM ensures that the closure is called with at least the absolute value of the number specified in nparamscheck(eg. nparamscheck == -3 will check that the function is called with at least 3 parameters). the hidden parameter 'this' is included in this number free variables aren't. If SQ_MATCHTYPEMASKSTRING is passed instead of the number of parameters, the function will automatically extrapolate the number of parameters to check from the typemask(eg. if the typemask is ".sn" is like passing 3).
<i>const SQChar * typemask</i>	defines a mask to validate the parameters types passed to the function. if the parameter is NULL no typechecking is applied(default).

remarks:

The typemask consists in a zero terminated string that represents the expected parameter type. The types are expressed as follows: 'o' null, 'i' integer, 'f' float, 'n' integer or float, 's' string, 't' table, 'a' array, 'u' userdata, 'c' closure and nativeclosure, 'g' generator, 'p' userpointer, 'v' thread, 'x' instance(class instance), 'y' class, 'b' bool. and '.' any type. The symbol '|' can be used as 'or' to accept multiple types on the same parameter. There isn't any limit on the number of 'or' that can be used. Spaces are ignored so can be inserted between types to increase readability. For instance to check a function that expects a table as 'this' a string as first parameter and a number or a userpointer as second parameter, the string would be "tsn|p" (table,string,number or userpointer). If the parameters mask contains less parameters than 'nparamscheck' the remaining parameters will not be typechecked.

eg.

```
//example
SQInteger testy(HSQIRRELVM v)
{
    SQUserPointer p;
    const SQChar *s;
    SQInteger i;
    //no type checking, if the call comply to the mask
    //surely the functions will succeed.
    sq_getuserdata(v,1,&p,NULL);
    sq_getstring(v,2,&s);
    sq_getinteger(v,3,&i);
    //... do something
    return 0;
}

//the reg code

//....stuff
sq_newclosure(v,testy,0);
//expects exactly 3 parameters(userdata,string,number)
sq_setparamscheck(v,3,_SC("usn"));
//....stuff
```

<b>sq_setreleasehook</b>
--------------------------

```
void sq_setreleasehook(HSQIRRELVM v, SQInteger idx, SQRELEASE-
HOOK hook);
```

sets the release hook of the userdata at position idx in the stack.

parameters:

<i>HSQIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	an index in the stack
<i>SQRELEASEHOOK hook</i>	a function pointer to the hook(see sample below)

remarks: the function hook is called by the VM before the userdata memory is deleted.

eg.

```
/* typedef SQInteger (*SQRELEASEHOOK)(SQUserPointer,SQInteger size); */
SQInteger my_release_hook(SQUserPointer p,SQInteger size)
{
    /* do something here */
    return 1;
}
```

**sq\_settypetag**

```
SQRESULT sq_settypetag(HSQUIRRELVM v, SQInteger idx, SQUserPointer typetag);
```

sets the typetag of the object(userdata or class) at position idx in the stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	an index in the stack
<i>SQUserPointer typetag</i>	an arbitrary SQUserPointer

return: a SQRESULT

**sq\_tobool**

```
void sq_tobool(HSQUIRRELVM v, SQInteger idx, SQBool * b);
```

gets the value at position idx in the stack as bool.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	an index in the stack
<i>SQBool * b</i>	A pointer to the bool that will store the value

remarks: if the object is not a bool the function converts the value too bool according to squirrel's rules. For instance the number 1 will result in true, and the number 0 in false.

**sq\_tostring**

```
void sq_tostring(HSQUIRRELVM v, SQInteger idx);
```

converts the object at position idx in the stack to string and pushes the resulting string in the stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	an index in the stack

## Calls

sq\_call

```
SQRESULT sq_call(HSQUIRRELVM v, SQInteger params, SQBool retval, SQBool raiseerror);
```

calls a closure or a native closure.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger params</i>	number of parameters of the function
<i>SQBool retval</i>	if true the function will push the return value in the stack
<i>SQBool raiseerror</i>	if true, if a runtime error occurs during the execution of the call, the vm will invoke the error handler.

return: a SQRESULT

remarks: the function pops all the parameters and leave the closure in the stack; if retval is true the return value of the closure is pushed. If the execution of the function is suspended through `sq_suspendvm()`, the closure and the arguments will not be automatically popped from the stack.

sq\_getlasterror

```
SQRESULT sq_getlasterror(HSQUIRRELVM v);
```

pushes the last error in the stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
----------------------	---------------

return: a SQRESULT

remarks: the pushed error descriptor can be any valid squirrel type.

sq\_getlocal

```
const SQChar * sq_getlocal(HSQUIRRELVM v, SQUnsignedInteger level, SQUnsignedInteger nseq);
```

Returns the name of a local variable given stackframe and sequence in the stack and pushes its current value. Free variables are treated as local variables, by `sq_getlocal()`, and will be returned as they would be at the base of the stack, just before the real local variables.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQUnsignedInteger level</i>	the function index in the calls stack, 0 is the current function
<i>SQUnsignedInteger nseq</i>	the index of the local variable in the stack frame (0 is 'this')

return: the name of the local variable if a variable exists at the given level/seq otherwise NULL.

`sq_reseterror`

void **sq\_reseterror**(HSQUIRRELVM v);

reset the last error in the virtual machine to null

parameters:

<i>HSQUIRRELVM v</i>	the target VM
----------------------	---------------

`sq_resume`

SQRESULT **sq\_resume**(HSQUIRRELVM v, SQBool retval, SQBool raiseerror);

resumes the generator at the top position of the stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQBool retval</i>	if true the function will push the return value in the stack
<i>SQBool raiseerror</i>	if true, if a runtime error occurs during the execution of the call, the vm will invoke the error handler.

return: a SQRESULT

remarks: if retval != 0 the return value of the generator is pushed.

`sq_throwerror`

SQRESULT **sq\_throwerror**(HSQUIRRELVM v, const SQChar \* err);

sets the last error in the virtual machine and returns the value that has to be returned by a native closure in order to trigger an exception in the virtual machine.

parameters:

*HSQUIRRELM v*      the target VM  
*const SQChar \* err*   the description of the error that has to be thrown

return:      the value that has to be returned by a native closure in order to throw an exception in the virtual machine.

## Objects manipulation

sq\_arrayappend

SQRESULT **sq\_arrayappend**(HSQUIRRELM v, SQInteger idx);

pops a value from the stack and pushes it in the back of the array at the position idx in the stack.

parameters:

*HSQUIRRELM v*    the target VM  
*SQInteger idx*    index of the target array in the stack

return:      a SQRESULT

remarks:      Only works on arrays.

sq\_arraypop

SQRESULT **sq\_arraypop**(HSQUIRRELM v, SQInteger idx);

pops a value from the back of the array at the position idx in the stack.

parameters:

*HSQUIRRELM v*    the target VM  
*SQInteger idx*    index of the target array in the stack

return:      a SQRESULT

remarks:      Only works on arrays.

sq\_arrayresize

SQRESULT **sq\_arrayresize**(HSQUIRRELM v, SQInteger idx, SQInteger newsize);

resizes the array at the position `idx` in the stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	index of the target array in the stack
<i>SQInteger newsize</i>	requested size of the array

return: a **SQRESULT**

remarks: Only works on arrays. if `newsize` is greater than the current size the new array slots will be filled with nulls.

sq\_arrayreverse

```
SQRESULT sq_arrayreverse(HSQUIRRELVM v, SQInteger idx);
```

reverse an array in place.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	index of the target array in the stack

return: a **SQRESULT**

remarks: Only works on arrays.

sq\_clear

```
SQRESULT sq_clear(HSQUIRRELVM v, SQInteger idx);
```

clears all the element of the table/array at position `idx` in the stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger idx</i>	index of the target object in the stack

return: a **SQRESULT**

remarks: Only works on tables and arrays.

sq\_clone

SQRESULT **sq\_clone**(HSQUIRRELM *v*, SQInteger *idx*);

Clones the table, array or class instance at the position *idx*, clones it and pushes the new object in the stack.

parameters:

*HSQUIRRELM v*    the target VM

*SQInteger idx*    index of the target object in the stack

return:            a SQRESULT

<b>sq_createslot</b>
----------------------

SQRESULT **sq\_createslot**(HSQUIRRELM *v*, SQInteger *idx*);

pops a key and a value from the stack and performs a set operation on the table or class that is at position *idx* in the stack, if the slot does not exists it will be created.

parameters:

*HSQUIRRELM v*    the target VM

*SQInteger idx*    index of the target table in the stack

return:            a SQRESULT

remarks:           invoke the `_newslot` metamethod in the table delegate. it only works on tables. [this function is deprecated since version 2.0.5 use `sq_newslot()` instead]

<b>sq_deleteslot</b>
----------------------

SQRESULT **sq\_deleteslot**(HSQUIRRELM *v*, SQInteger *idx*, SQBool *pushval*);

pops a key from the stack and delete the slot indexed by it from the table at position *idx* in the stack, if the slot does not exists nothing happens.

parameters:

*HSQUIRRELM v*    the target VM

*SQInteger idx*    index of the target table in the stack

*SQBool pushval*    if this param is true the function will push the value of the deleted slot.

return:            a SQRESULT

remarks:           invoke the `_delslot` metamethod in the table delegate. it only works on tables.



sq\_get

SQRESULT **sq\_get**(HSQUIRRELVM *v*, SQInteger *idx*);

pops a key from the stack and performs a get operation on the object at the position *idx* in the stack, and pushes the result in the stack.

parameters:

*HSQUIRRELVM v* the target VM

*SQInteger idx* index of the target object in the stack

return: a SQRESULT

remarks: this call will invokes the delegation system like a normal dereference it only works on tables, arrays and userdata. if the function fails nothing will be pushed in the stack.

sq\_getattributes

SQRESULT **sq\_getattributes**(HSQUIRRELVM *v*, SQInteger *idx*);

Gets the attribute of a class member. The function pops a key from the stack and pushes the attribute of the class member indexed by they key from class at position *idx* in the stack. If key is null the function gets the class level attribute.

parameters:

*HSQUIRRELVM v* the target VM

*SQInteger idx* index of the target class in the stack

return: a SQRESULT

sq\_getclass

SQRESULT **sq\_getclass**(HSQUIRRELVM *v*, SQInteger *idx*);

pushes the class of the 'class instance' at stored position *idx* in the stack.

parameters:

*HSQUIRRELVM v* the target VM

*SQInteger idx* index of the target class instance in the stack

return: a SQRESULT

`sq_getdelegate`

SQRESULT **sq\_getdelegate**(HSQUIRRELVM *v*, SQInteger *idx*);

pushes the current delegate of the object at the position *idx* in the stack.

parameters:

*HSQUIRRELVM v*    the target VM

*SQInteger idx*    index of the target object in the stack

return:            a SQRESULT

`sq_getfreevariable`

const SQChar \* **sq\_getfreevariable**(HSQUIRRELVM *v*, SQInteger *idx*, SQInteger *nval*);

gets the value of the free variable of the closure at the position *idx* in the stack.

parameters:

*HSQUIRRELVM v*    the target VM

*SQInteger idx*    index of the target object in the stack(closure)

*SQInteger nval*    0 based index of the free variable(relative to the closure).

return:            the name of the free variable for pure squirrel closures. NULL in case of error or if the index of the variable is out of range.

remarks:           The function will always fail with C native closures.

`sq_getweakrefval`

SQRESULT **sq\_getweakrefval**(HSQUIRRELVM *v*, SQInteger *idx*);

pushes the object pointed by the weak reference at position *idx* in the stack.

parameters:

*HSQUIRRELVM v*    the target VM

*SQInteger idx*    index of the target weak reference

return:            a SQRESULT

remarks:           if the function fails, nothing is pushed in the stack.

sq\_instanceof

```
SQBool sq_instanceof(HSQUIRRELM v);
```

Determines if an object is an instance of a certain class. Expects an instance and a class in the stack.

parameters:

*HSQUIRRELM v*    the target VM

return:            SQTrue if the instance at position -2 in the stack is an instance of the class object at position -1 in the stack.

remarks:           The function doesn't pop any object from the stack.

sq\_newslot

```
SQRESULT sq_newslot(HSQUIRRELM v, SQInteger idx, SQBool bstatic);
```

pops a key and a value from the stack and performs a set operation on the table or class that is at position idx in the stack, if the slot does not exist it will be created.

parameters:

*HSQUIRRELM v*    the target VM

*SQInteger idx*    index of the target table in the stack

*SQBool bstatic*   if SQTrue creates a static member. This parameter is only used if the target object is a class.

return:            a SQRESULT

remarks:           Invokes the `_newslot` metamethod in the table delegate. it only works on tables.

sq\_next

```
SQRESULT sq_next(HSQUIRRELM v, SQInteger idx);
```

Pushes in the stack the next key and value of an array, table or class slot. To start the iteration this function expects a null value on top of the stack; at every call the function will substitute the null value with an iterator and push key and value of the container slot. Every iteration the application has to pop the previous key and value but leave the iterator (that is used as reference point for the next iteration). The function will fail when all slots have been iterated (see Tables and arrays manipulation).

parameters:

*HSQUIRRELM v*    the target VM

*SQInteger idx* index of the target object in the stack

return: a SQRESULT

`sq_rawdeleteslot`

SQRESULT **sq\_rawdeleteslot**(HSQUIRRELVM *v*, SQInteger *idx*, SQ-Bool *pushval*);

Deletes a slot from a table without employing the `_delslot` metamethod. pops a key from the stack and delete the slot indexed by it from the table at position *idx* in the stack, if the slot does not exists nothing happens.

parameters:

*HSQUIRRELVM v* the target VM

*SQInteger idx* index of the target table in the stack

*SQBool pushval* if this param is true the function will push the value of the deleted slot.

return: a SQRESULT

`sq_rawget`

SQRESULT **sq\_rawget**(HSQUIRRELVM *v*, SQInteger *idx*);

pops a key from the stack and performs a get operation on the object at position *idx* in the stack, without employing delegation or metamethods.

parameters:

*HSQUIRRELVM v* the target VM

*SQInteger idx* index of the target object in the stack

return: a SQRESULT

remarks: Only works on tables and arrays.

`sq_rawset`

SQRESULT **sq\_rawset**(HSQUIRRELVM *v*, SQInteger *idx*);

pops a key and a value from the stack and performs a set operation on the object at position *idx* in the stack, without employing delegation or metamethods.

parameters:

*HSQUIRRELVm* *v* the target VM

*SQInteger* *idx* index of the target object in the stack

return: a SQRRESULT

remarks: it only works on tables and arrays. if the function fails nothing will be pushed in the stack.

<code>sq_set</code>
---------------------

SQRRESULT **sq\_set**(HSQUIRRELVm *v*, SQInteger *idx*);

pops a key and a value from the stack and performs a set operation on the object at position *idx* in the stack.

parameters:

*HSQUIRRELVm* *v* the target VM

*SQInteger* *idx* index of the target object in the stack

return: a SQRRESULT

remarks: this call will invoke the delegation system like a normal assignment, it only works on tables, arrays and userdata.

<code>sq_setattributes</code>
-------------------------------

SQRRESULT **sq\_setattributes**(HSQUIRRELVm *v*, SQInteger *idx*);

Sets the attribute of a class member. The function pops a key and a value from the stack and sets the attribute (indexed by the key) on the class at position *idx* in the stack. If key is null the function sets the class level attribute. If the function succeeds, the old attribute value is pushed in the stack.

parameters:

*HSQUIRRELVm* *v* the target VM

*SQInteger* *idx* index of the target class in the stack.

return: a SQRRESULT

<code>sq_setdelegate</code>
-----------------------------

SQRRESULT **sq\_setdelegate**(HSQUIRRELVm *v*, SQInteger *idx*);

pops a table from the stack and sets it as delegate of the object at the position `idx` in the stack.

parameters:

*HSQUIRRELVM v* the target VM

*SQInteger idx* index of the target object in the stack

return: a SQRRESULT

remarks: to remove the delgate from an object is necessary to use null as delegate instead of a table.

`sq_setfreevariable`

```
SQRRESULT sq_setfreevariable(HSQUIRRELVM v, SQInteger idx, SQInteger nval);
```

pops a value from the stack and sets it as free variable of the closure at the position `idx` in the stack.

parameters:

*HSQUIRRELVM v* the target VM

*SQInteger idx* index of the target object in the stack

*SQInteger nval* 0 based index of the free variable(relative to the closure).

return: a SQRRESULT

`sq_weakref`

```
void sq_weakref(HSQUIRRELVM v, SQInteger idx);
```

pushes a weak reference to the object at position `idx` in the stack.

parameters:

*HSQUIRRELVM v* the target VM

*SQInteger idx* index to the target object in the stack

return: a SQRRESULT

remarks: if the object at `idx` position is an integer,float,bool or null the object itself is pushed instead of a weak ref.

## Bytecode serialization

`sq_readclosure`

```
SQRESULT sq_readclosure(HSQUIRRELVM v, SQREADFUNC readf, SQUserPointer up);
```

serialize (read) a closure and pushes it on top of the stack, the source is user defined through a read callback.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQREADFUNC readf</i>	pointer to a read function that will be invoked by the vm during the serialization.
<i>SQUserPointer up</i>	pointer that will be passed to each call to the read function

return: a SQRESULT

`sq_writeclosure`

```
SQRESULT sq_writeclosure(HSQUIRRELVM v, SQWRITEFUNC writef, SQUserPointer up);
```

serialize(write) the closure on top of the stack, the destination is user defined through a write callback.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQWRITEFUNC writef</i>	pointer to a write function that will be invoked by the vm during the serialization.
<i>SQUserPointer up</i>	pointer that will be passed to each call to the write function

return: a SQRESULT

remarks: closures with free variables cannot be serialized

## Raw object handling

`sq_addrf`

```
void sq_addrf(HSQUIRRELVM v, HSQOBJECT * po);
```

adds a reference to an object handler.

parameters:

*HSQUIRRELVM v*      the target VM  
*HSQOBJECT \* po*    pointer to an object handler

`sq_getobjtypetag`

`SQRESULT sq_getobjtypetag(HSQOBJECT * o, SQUserPointer * typetag);`

gets the typetag of a raw object reference(userdata or class).

parameters:

*HSQOBJECT \* o*                      pointer to an object handler  
*SQUserPointer \* typetag*    a pointer to the variable that will store the tag

return:                      a SQRESULT

remarks:                    the function works also with instances. if the taget object is an instance, the typetag of it's base class is fetched.

`sq_getstackobj`

`SQRESULT sq_getstackobj(HSQUIRRELVM v, SQInteger idx, HSQOBJECT * po);`

gets an object from the stack and stores it in a object handler.

parameters:

*HSQUIRRELVM v*      the target VM  
*SQInteger idx*      index of the target object in the stack  
*HSQOBJECT \* po*    pointer to an object handler

return:                      a SQRESULT

`sq_objtobool`

`SQBool sq_objtobool(HSQOBJECT * po);`

return the bool value of a raw object reference.

parameters:

*HSQOBJECT \* po*    pointer to an object handler



remarks: If the object is not a bool will always return false.

`sq_objtfloat`

```
SQFloat sq_objtfloat(HSQOBJECT * po);
```

return the float value of a raw object reference.

parameters:

*HSQOBJECT \* po* pointer to an object handler

remarks: If the object is an integer will convert it to float. If the object is not a number will always return 0.

`sq_objtinteger`

```
SQInteger sq_objtinteger(HSQOBJECT * po);
```

return the integer value of a raw object reference.

parameters:

*HSQOBJECT \* po* pointer to an object handler

remarks: If the object is a float will convert it to integer. If the object is not a number will always return 0.

`sq_objtstring`

```
const SQChar * sq_objtstring(HSQOBJECT * po);
```

return the string value of a raw object reference.

parameters:

*HSQOBJECT \* po* pointer to an object handler

remarks: If the object doesn't reference a string it returns NULL.

`sq_pushobject`

```
void sq_pushobject(HSQUIRRELVM v, HSQOBJECT obj);
```

push an object referenced by an object handler into the stack.

parameters:

*HSQUIRRELVm v* the target VM

*HSQOBJECT obj* object handler

`sq_release`

SQBool **sq\_release**(HSQUIRRELVm v, HSQOBJECT \* po);

remove a reference from an object handler.

parameters:

*HSQUIRRELVm v* the target VM

*HSQOBJECT \* po* pointer to an object handler

return: SQTrue if the object handler released has lost all its references (the ones added with sq\_addref). SQFalse otherwise.

remarks: the function will reset the object handler to null when it loses all references.

`sq_resetobject`

void **sq\_resetobject**(HSQUIRRELVm v, HSQOBJECT \* po);

resets(initialize) an object handler.

parameters:

*HSQUIRRELVm v* the target VM

*HSQOBJECT \* po* pointer to an object handler

remarks: Every object handler has to be initialized with this function.

## Debug interface

`sq_setdebughook`

void **sq\_setdebughook**(HSQUIRRELVm v);

pops a closure from the stack and sets it as debug hook. on.

parameters:

*HSQUIRRELVM v* the target VM

remarks: In order to receive a 'per line' callback, is necessary to compile the scripts with the line informations. Without line informations activated, only the 'call/return' callbacks will be invoked.

<code>sq_stackinfos</code>
----------------------------

```
SQRESULT sq_stackinfos(HSQUIRRELVM v, SQInteger level, SQStackInfos * si);
```

retrieve the calls stack informations of a ceratain level in the calls stack.

parameters:

<i>HSQUIRRELVM v</i>	the target VM
<i>SQInteger level</i>	calls stack level
<i>SQStackInfos * si</i>	pointer to the SQStackInfos structure that will store the stack informations

return: a SQRESULT.

---

# Index

## Symbols

?: operator, 13  
\_charsize\_, 38  
\_intsize\_, 38  
\_version\_, 38

## A

arithmetic operators, 13  
array, 37  
    append, 41  
    clear, 42  
    extend, 41  
    insert, 41  
    len, 41  
    pop, 41  
    push, 41  
    remove, 41  
    resize, 41  
    reverse, 42  
    slice, 42  
    sort, 41  
    top, 41  
    tostring, 42  
    weakref, 42  
array constructor, 17  
arrays, 18  
assert, 37  
assignment(=), 12

## B

binding an environment to a function, 20  
bitwise Operators, 15  
block statement, 8  
bool  
    tofloat, 39  
    tointeger, 39  
    tostring, 39  
    weakref, 39  
break statement, 10

## C

class  
    getattributes, 43  
    instance, 43  
    rawin, 43  
    setattributes, 43  
    tostring, 43  
    weakref, 43  
class attributes, 23  
class declaration, 11, 21  
class instance metamethods, 27  
class instances, 24

classes, 21  
clone, 16  
collectgarbage, 38  
comma operator, 14  
comments, 3  
compilestring, 37  
const statement, 12  
constants, 28  
continue statement, 10

## D

data types, 3  
delegate, 16  
delegation, 33  
do/while statement, 9

## E

enableddebuginfo, 37  
enum statement, 12  
execution context, 6  
expression statement, 12  
expressions, 12

## F

float  
    tochar, 39  
    tointeger, 39  
    tostring, 39  
    weakref, 39  
for loop, 9  
foreach loop, 10  
free variables, 21  
function  
    acall, 42  
    bindenv, 43  
    call, 42  
    pacall, 42  
    pcall, 42  
    tostring, 43, 43  
    weakref, 42  
function declaration, 11  
functions, 18  
    calls, 20  
    declaration, 18

## G

generator  
    getstatus, 44  
    tostring, 44  
    weakref, 44  
generators, 27  
getconsttable, 37  
getroottable, 37  
getstackinfos, 38

## I

identifiers, 2  
if/else statement, 8  
in operator, 14  
inheritance, 25  
instance

    getclass, 43  
    rawin, 43  
    tostring, 44  
    weakref, 43

instanceof operator, 14

integer

    tochar, 39  
    tofloat, 38, 39  
    tointeger, 39  
    tostring, 39  
    weakref, 39

## K

keywords, 2

## L

literals, 2  
local variables declaration, 11  
logical operators, 13

## M

metamethods, 33

    \_add, 35  
    \_call, 36  
    \_cloned, 36  
    \_cmp, 35  
    \_delslot, 34  
    \_div, 35  
    \_get, 34  
    \_inherited, 36  
    \_modulo, 35  
    \_mul, 35  
    \_newmember, 36  
    \_newslot, 34  
    \_nexti, 36  
    \_set, 34  
    \_sub, 35  
    \_tostring, 36  
    \_typeof, 35  
    \_unm, 35

## N

new slot(<-), 12  
newthread, 38

## O

operators, 2, 13  
operators precedence, 15

## P

print, 37

## R

relational operators, 13  
return statement, 10

## S

setconsttable, 37  
setdebughook, 37  
seterrorhandler, 37  
setroottable, 37  
sq\_addrf, 89  
sq\_arrayappend, 80  
sq\_arraypop, 80  
sq\_arrayresize, 80  
sq\_arrayreverse, 81  
sq\_bindenv, 65  
sq\_call, 78  
sq\_clear, 81  
sq\_clone, 81  
sq\_close, 56  
sq\_cmp, 63  
sq\_compile, 61  
sq\_compilebuffer, 61  
sq\_createinstance, 65  
sq\_createslot, 82  
sq\_deleteslot, 82  
sq\_enabledebuginfo, 62  
sq\_get, 83  
sq\_getattributes, 83  
sq\_getbool, 66  
sq\_getclass, 83  
sq\_getclosureinfo, 66  
sq\_getdelegate, 84  
sq\_getfloat, 67  
sq\_getforeignptr, 56  
sq\_getfreevariable, 84  
sq\_getinstanceup, 67  
sq\_getinteger, 67  
sq\_getlasterror, 78  
sq\_getlocal, 78  
sq\_getobjtypetag, 90  
sq\_getprintfunc, 56  
sq\_getscratchpad, 68  
sq\_getsize, 68  
sq\_getstackobj, 90  
sq\_getstring, 68  
sq\_getthread, 69  
sq\_gettop, 63  
sq\_gettype, 69  
sq\_gettypetag, 69  
sq\_getuserdata, 70  
sq\_getuserpointer, 70  
sq\_getvmstate, 56  
sq\_getweakrefval, 84  
sq\_instanceof, 85  
sq\_move, 57  
sq\_newarray, 70  
sq\_newclass, 71

sq\_newclosure, 71  
sq\_newslot, 85  
sq\_newtable, 71  
sq\_newthread, 57  
sq\_newuserdata, 72  
sq\_next, 85  
sq\_notifyallexceptions, 62  
sq\_objtobool, 90  
sq\_objtfloat, 91  
sq\_objtointeger, 91  
sq\_objtostring, 91  
sq\_open, 57  
sq\_pop, 63  
sq\_poptop, 64  
sq\_push, 64  
sq\_pushbool, 72  
sq\_pushconsttable, 58  
sq\_pushfloat, 72  
sq\_pushinteger, 72  
sq\_pushnull, 73  
sq\_pushobject, 91  
sq\_pushregistrytable, 58  
sq\_pushroottable, 58  
sq\_pushstring, 73  
sq\_pushuserpointer, 73  
sq\_rawdeleteslot, 86  
sq\_rawget, 86  
sq\_rawset, 86  
sq\_readclosure, 89  
sq\_release, 92  
sq\_remove, 64  
sq\_reservestack, 64  
sq\_reseterror, 79  
sq\_resetobject, 92  
sq\_resume, 79  
sq\_set, 87  
sq\_setattributes, 87  
sq\_setclassudsize, 74  
sq\_setcompilererrorhandler, 63  
sq\_setconsttable, 58  
sq\_setdebughook, 92  
sq\_setdelegate, 87  
sq\_seterrorhandler, 59  
sq\_setforeignptr, 59  
sq\_setfreevariable, 88  
sq\_setinstanceup, 74  
sq\_setnativeclosurename, 74  
sq\_setparamscheck, 75  
sq\_setprintfunc, 59  
sq\_setreleasehook, 76  
sq\_setroottable, 60  
sq\_settop, 65  
sq\_settypetag, 77  
sq\_stackinfos, 93  
sq\_suspendvm, 60  
sq\_throwerror, 79  
sq\_tobool, 77  
sq\_tostring, 77

## T

sq\_wakeupvm, 60  
sq\_weakref, 88  
sq\_writeclosure, 89  
statements, 8  
static variables, 23  
string  
  find, 40  
  len, 39  
  slice, 40  
  tfloat, 40  
  tinteger, 40  
  tolower, 40  
  tostring, 40  
  toupper, 40  
  weakref, 40  
switch statement, 9  
  
table  
  clear, 41  
  len, 40  
  rawdelete, 40  
  rawget, 40  
  rawin, 41  
  rawset, 40  
  tostring, 41  
  weakref, 41  
table constructor, 15  
tables, 17  
  slot creation, 17  
  slot deletion, 18  
tail recursion, 21  
thread  
  call, 44  
  getstatus, 44  
  tostring, 44  
  wakeup, 44  
  weakref, 44  
threads, 30  
throw statement, 12  
true and false, 8  
try/catch statement, 11  
type, 38  
typeof operator, 14

## U

using threads, 30

## V

variables, 6

## W

weak references, 32  
weakref  
  ref, 44  
  tostring, 44  
  weakref, 44

## Y

while statement, 8

yield statement, 11