

DRAFT

NE2001: CODE DESCRIPTION

J. M. CORDES
 Astronomy Department and NAIC, Cornell University, Ithaca, NY 14853
 cordes@spacenet.tn.cornell.edu

T. JOSEPH W. LAZIO
 Naval Research Lab, Code 7213, Washington, D.C. 20375-5351
 lazio@rsd.nrl.navy.mil

COMPILING INSTRUCTIONS (UNIX/LINUX)

1. Unpack the tar file through `tar xvf NE2001.tar` in the directory where you would like the code. The unpacked files should include:

```
src.NE2001/OOREADME (plain ascii version of this description)
src.NE2001/Makefile
src.NE2001/NE2001.f
src.NE2001/code.ps (postscript version of this description)
src.NE2001/code.dvi (dvi file of this description)
src.NE2001/density.NE2001.f
src.NE2001/dmdsm.NE2001.f
src.NE2001/neLISM.NE2001.f
src.NE2001/neclumpN.f
src.NE2001/run_NE2001.pl
src.NE2001/scattering98.f
input.NE2001/gal01.inp
input.NE2001/ne_arms_log_mod.inp
input.NE2001/ne_gc.inp
input.NE2001/neclumpN.dat
input.NE2001/nelism.inp
input.NE2001/nevoidN.dat
```

2. Edit `Makefile` and set the value of `BINDIR` to the destination where you would like the executable to reside.
3. Compile the code by typing `make`.
4. Copy the files in `input.NE2001` to the directory where you will execute the program `NE2001`. The perl script `run_NE2001.pl`, if used, also needs to be executed in the same directory containing the input files. The perl script needs to be edited to designate the location of the executable for `NE2001`.

DESCRIPTION OF FORTRAN CODE

Our model is implemented in a set of Fortran routines that are similar in functionality to those presented in TC93, but represent a complete revision according to the new features presented in the main text. A master program `NE2001` evaluates the model by returning the integrated measures (DM, SM, etc.) and/or distance given an input direction and DM or distance. Integrations are performed in the subroutine `dmdsm`, which evaluates the model by making calls to subroutine `density2001`. Copies of all code and necessary input files are available over the Internet at www.astro.cornell.edu/cordes/NE2001 and NRL URL for mirror site here. The code is packaged as a ‘tar’ file, `NE2001.tar`, that includes a makefile for compiling the code in a Unix/Linux environment.

A description of the functionality of the code is as follows: The call to `dmdsm` is of the form

```
call dmdsm(l,b,ndir,dm,dist,limit,sm,smtau,stheta,smiso) .
```

Here the input data include Galactic longitude and latitude `l` and `b` (in radians) and a flag `ndir` indicating whether distance is to be calculated from dispersion measure (`ndir ≥ 0`), or *vice-versa* (`ndir < 0`). In either case, `dm` and `dist` have units of pc cm^{-3} and kpc , respectively. A flag `limit` is set if `ndir ≥ 0` and the model distance is a lower limit; this will occur, for example, if a large `dm` is specified at high galactic latitude. The subroutine also returns four estimates of scattering measure, all having units $\text{kpc m}^{-20/3}$. The first, `sm`, conforms to the definition $\text{SM} = \int_0^D ds C_n^2(s)$ with uniform weighting along the line of sight. The next two estimates, `smtau` and `stheta`, correspond to line-of-sight weightings appropriate for temporal and angular broadening of galactic sources, respectively. Temporal broadening emphasizes scattering material midway between source and observer, while angular broadening favors material closest to the observer; see Eqs. (A14, B2) of Cordes, Weisberg, & Boriakoff (1985). The last estimate, `smiso` uses the weighting appropriate for calculating the isoplanatic angle of scattering.

Integrations in `dmdsm` involve evaluations of the model at a given Galactic location (x, y, z) through a call to subroutine `density_2001`, where x, y, z are Galactocentric Cartesian coordinates, measured in kiloparsecs, with the axes parallel to $(l, b) = (90^\circ, 0^\circ)$, $(180^\circ, 0^\circ)$, and $(0^\circ, 90^\circ)$;

```
call density_2001(x,y,z,
. ne1,ne2,nea,negc,nelism,necN,nevN,
. F1, F2, Fa, Fgc, Flism, FcN, FvN,
. whicharm, wlism, wldr, wlhb, wlsb, wloopI,
. hitclump, hitvoid, wvoid).
```

The routine returns values for the electron density in seven components (`ne1`, ..., `nevN`), the corresponding ‘F’ parameters (`F1`, ..., `FvN`), followed by a series of integer-valued flags. The meanings of these flags are as follows:

1. `whicharm` = 0, ..., 5 indicates which spiral arm contributes to the density, with numbering as in the text and where a zero value denotes an interarm region.
2. `wlism`, `wldr`, `wlhb`, `wlsb` and `wloopI` take on values of 0 or 1 as described in the Appendix of the paper describing NE2001.
3. `hitclump` denotes whether a clump has been hit; if so, then `hitclump` denotes the clump number in the table of clumps; if not, `hitclump` = 0.
4. `hitvoid` works in the same fashion for voids; additionally, `wvoid` = 0, 1 is used in evaluating the total density and indicates if a void has been hit (`wvoid` = 1).

The calling program is executed using command-line arguments that specify the galactic longitude and latitude, an input DM or distance value, and a flag (`ndir`) that specifies whether a distance is calculated from DM (`ndir` \geq 0) or a DM calculated from an input distance (`ndir` < 0):

```
Usage: NE2001 l b DM/D ndir
        l (deg)
        b (deg)
        DM/D (pc cm-3 or kpc)
        ndir = 1 (DM->D)      -1 (D->DM)
```

Program NE2001 uses output from `dmdsm` to calculate scattering and scintillation quantities by making suitable calls to a series of functions. In all cases, input distances, scattering measures, frequencies and velocities are in standard units (kpc, kpc m^{-20/3}, GHz and km s⁻¹):

1. `function tauiss(d,sm,nu)`: calculates the pulse broadening time, τ_d (ms).
2. `function scintbw(d,sm,nu)`: calculates the scintillation bandwidth, $\Delta\nu_d$ (MHz).
3. `function scintime(sm,nu,vperp)`: calculates the scintillation time, Δt_{ISS} (sec) (Cordes & Lazio 1991; Cordes & Rickett 1998).
4. `function specbroad(sm,nu,vperp)`: calculates the spectral broadening, $\Delta\nu_b$ (Hz), that is proportional to the reciprocal of the scintillation time (Cordes & Lazio 1991).
5. `function theta_xgal(sm,nu)`: calculates the angular broadening, θ_d (mas), appropriate for the scattering geometry for an extragalactic source (mas).
6. `function theta_gal(sm,nu)`: calculates the angular broadening, θ_d (mas), of a Galactic source (mas).
7. `function em(sm)`: calculates the emission measure, EM (pc cm⁻⁶), associated with the scattering measure; note that the value calculated assumes a particular outer scale for a Kolmogorov wavenumber spectrum and represents a lower bound on EM (see text).
8. `function theta_iso(smiso,nu)`: calculates the isoplanatic angle, θ_{iso} (mas), the region on the sky over which scintillations are correlated.
9. `function transition_frequency(sm,smtau,smtheta,dintegrate)`: calculates the frequency of transition, ν_{trans} (GHz), between the weak and strong scattering regimes.

Sample output for $\ell = 45^\circ$, $b = 5^\circ$, and DM = 50 pc cm⁻³ is:

```

NE2001.new 45 5 50 1
#NE2001 input: 4 parameters
  45.0000      1      (deg)      GalacticLongitude
   5.0000      b      (deg)      GalacticLatitude
  50.0000      DM/D      (pc-cm-3_or_kpc)      Input_DM_or_Distance
       1      ndir      1:DM->D;-1:D->DM      Which?(DM_or_D)
#NE2001 output: 14 values
  2.6365      DIST      (kpc)      ModelDistance
  50.0000      DM      (pc-cm-3)      DispersionMeasure
  4.3578      DMz      (pc-cm-3)      DM_Zcomponent
0.3528E-03      SM      (kpc-m-20/3)      ScatteringMeasure
0.2367E-03      SMtau      (kpc-m-20/3)      SM_PulseBroadening
0.7719E-04      SMtheta      (kpc-m-20/3)      SM_GalAngularBroadening
0.1307E-02      SMiso      (kpc-m-20/3)      SM_IsoplanaticAngle
0.1921E+00      EM      (pc-cm-6)      EmissionMeasure_from_SM
0.1293E-03      TAU      (ms)      PulseBroadening @1GHz
0.1428E+01      SBW      (MHz)      ScintBW @1GHz
0.4943E+03      SCINTIME      (s)      ScintTime @1GHz @100 km/s
0.2420E+00      THETA_G      (mas)      AngBroadeningGal @1GHz
0.1086E+01      THETA_X      (mas)      AngBroadeningXgal @1GHz
  14.02      NU_T      (GHz)      TransitionFrequency

```

The Fortran program can be run using a perl script and where an individual field can be selected for output:

```
run_NE2001.pl
```

Usage:

```

run_NE2001      1      b      DM/D      ndir      field
                  deg deg      pc-cm-3      1,-1      D etc
                  or kpc

```

Possible Fields (case insensitive):

Dist, DM, SM, EM, TAU, SBW, SCINTIME, THETA_G, THETA_X, NU_T, ALL