



Using VoltDB

Abstract

This book explains how to use VoltDB to design, build, and run high performance applications.

V3.5

Using VoltDB

V3.5

Copyright © 2008-2013 VoltDB, Inc.

The text and illustrations in this document are licensed under the terms of the GNU Affero General Public License Version 3 as published by the Free Software Foundation. See the GNU Affero General Public License (<http://www.gnu.org/licenses/>) for more details.

Some of the features described in this documentation are specific to the VoltDB Enterprise Edition, which is distributed by VoltDB, Inc. under a commercial license. Many of the core VoltDB database features described herein are also part of the VoltDB Community Edition, which is licensed under the GNU Affero Public License 3 as published by the Free Software Foundation. Your rights to access and use VoltDB features described herein are defined by the license you received when you acquired the software.

This document was generated on August 07, 2013.

Table of Contents

Preface	xi
1. Overview	1
1.1. What is VoltDB?	1
1.2. Who Should Use VoltDB	1
1.3. How VoltDB Works	2
1.3.1. Partitioning	2
1.3.2. Serialized (Single-Threaded) Processing	2
1.3.3. Partitioned vs. Replicated Tables	3
1.3.4. Ease of Scaling to Meet Application Needs	4
2. Installing VoltDB	5
2.1. Operating System and Software Requirements	5
2.2. Installing VoltDB	5
2.2.1. Upgrading an Existing VoltDB Installation	6
2.2.2. Performing a System-Wide Installation on Ubuntu	6
2.2.3. Building a New VoltDB Distribution Kit	7
2.3. Setting Up Your Environment	7
2.4. What is Included in the VoltDB Distribution	7
2.5. VoltDB in Action: Running the Sample Applications	8
3. Designing Your VoltDB Application	10
3.1. Designing the Database	10
3.1.1. Partitioning Database Tables	12
3.1.2. Replicating Tables	13
3.2. Designing the Data Access (Stored Procedures)	13
3.2.1. Writing VoltDB Stored Procedures	14
3.2.2. VoltDB Stored Procedures and Determinism	14
3.2.3. The Anatomy of a VoltDB Stored Procedure	15
3.2.4. Partitioning Stored Procedures	21
3.3. Designing the Application Logic	23
3.3.1. Connecting to the VoltDB Database	23
3.3.2. Invoking Stored Procedures	24
3.3.3. Invoking Stored Procedures Asynchronously	25
3.3.4. Closing the Connection	26
3.4. Handling Errors	26
3.4.1. Interpreting Execution Errors	26
3.4.2. Handling Timeouts	28
3.4.3. Interpreting Other Errors	29
4. Simplifying Application Development	32
4.1. Default Procedures for Partitioned Tables	32
4.2. Shortcut for Defining Simple Stored Procedures	33
4.3. Verifying Expected Query Results	34
5. Building Your VoltDB Application	35
5.1. Compiling the Client Application and Stored Procedures	35
5.2. Declaring the Stored Procedures	35
5.3. Building the Application Catalog	36
6. Running Your VoltDB Application	37
6.1. Defining the Cluster Configuration	37
6.1.1. Determining How Many Partitions to Use	38
6.1.2. Configuring Paths for Runtime Features	38
6.1.3. Verifying your Hardware Configuration	39
6.2. Starting a VoltDB Database for the First Time	39
6.2.1. Simplifying Startup on a Cluster	40

6.2.2. How VoltDB Database Startup Works	41
6.3. Starting VoltDB Client Applications	41
6.4. Shutting Down a VoltDB Database	41
6.5. Stopping and Restarting a VoltDB Database	42
6.5.1. Save and Restore	42
6.5.2. Command Logging and Recovery	42
6.6. Modes of Operation	43
6.6.1. Admin Mode	43
6.6.2. Starting the Database in Admin Mode	44
7. Updating Your VoltDB Database	45
7.1. Planning Your Application Updates	45
7.2. Updating the Database Schema on a Running Database	45
7.2.1. Validating the Updated Catalog	46
7.2.2. Managing the Update Process	46
7.3. Updating the Database Using Save and Restore	47
7.4. Updating the Hardware Configuration	47
8. Security	49
8.1. How Security Works in VoltDB	49
8.2. Enabling Authentication and Authorization	49
8.3. Defining Users and Roles	49
8.4. Assigning Access to Stored Procedures	50
8.5. Allowing Access to System Procedures, Ad Hoc Queries, and Default Procedures	51
9. Saving & Restoring a VoltDB Database	52
9.1. Performing a Manual Save and Restore of a VoltDB Cluster	52
9.1.1. How to Save the Contents of a VoltDB Database	53
9.1.2. How to Restore the Contents of a VoltDB Database	53
9.1.3. Changing the Database Schema or Cluster Configuration Using Save and Re- store	53
9.2. Scheduling Automated Snapshots	54
9.3. Managing Snapshots	55
9.4. Special Notes Concerning Save and Restore	56
10. Command Logging and Recovery	57
10.1. How Command Logging Works	57
10.2. Enabling Command Logging	58
10.3. Configuring Command Logging for Optimal Performance	58
10.3.1. Log Size	59
10.3.2. Log Frequency	59
10.3.3. Synchronous vs. Asynchronous Logging	59
10.3.4. Hardware Considerations	60
11. Availability	62
11.1. How K-Safety Works	62
11.2. Enabling K-Safety	63
11.2.1. What Happens When You Enable K-Safety	64
11.2.2. Calculating the Appropriate Number of Nodes for K-Safety	64
11.3. Recovering from System Failures	65
11.3.1. What Happens When a Node Rejoins the Cluster	65
11.3.2. Rejoining a "Live" Cluster	66
11.3.3. Where and When Recovery May Fail	66
11.4. Avoiding Network Partitions	67
11.4.1. K-Safety and Network Partitions	67
11.4.2. Using Network Fault Protection	68
12. Database Replication	70
12.1. How Database Replication Works	70
12.1.1. Starting Replication	71

12.1.2. Replication and Existing Databases	71
12.1.3. Database Replication and Disaster Recovery	72
12.1.4. Database Replication and Completeness	73
12.1.5. Database Replication and Read-only Clients	73
12.2. Database Replication in Action	74
12.2.1. Starting Replication	74
12.2.2. Stopping Replication	75
12.2.3. Promoting the Replica When the Master Becomes Unavailable	76
12.2.4. Managing Database Replication	76
12.3. Using the Sample Applications to Demonstrate Replication	77
12.3.1. Replicating the Voter Sample Using the Enterprise Manager	78
12.3.2. Replicating the Voter Sample Using the Command Line	78
13. Exporting Live Data	80
13.1. Understanding Export	80
13.2. Planning your Export Strategy	81
13.3. Identifying Export Tables in the Schema	82
13.4. Configuring Export in the Deployment File	83
13.5. How Export Works	83
13.5.1. Export Overflow	84
13.5.2. Persistence Across Database Sessions	85
13.6. Using the Export Clients	85
13.6.1. Running the Export Client on the Database Server	85
13.6.2. Running the Export Client Remotely	88
13.7. The Export-to-JDBC Client	89
13.8. The Export-to-File Client	89
13.8.1. Understanding the Export-to-File Client Output	89
13.8.2. The Export-to-File Client Command Line	90
13.9. The Export-to-Hadoop Client	92
13.9.1. The Export-to-Hadoop Client Command Line	92
14. Logging and Analyzing Activity in a VoltDB Database	94
14.1. Introduction to Logging	94
14.2. Creating the Logging Configuration File	94
14.3. Enabling Logging for VoltDB	96
14.4. Customizing Logging in the VoltDB Enterprise Manager	96
14.5. Changing the Configuration on the Fly	96
15. Using VoltDB with Other Programming Languages	98
15.1. C++ Client Interface	98
15.1.1. Writing VoltDB Client Applications in C++	98
15.1.2. Creating a Connection to the Database Cluster	99
15.1.3. Invoking Stored Procedures	99
15.1.4. Invoking Stored Procedures Asynchronously	100
15.1.5. Interpreting the Results	101
15.2. JSON HTTP Interface	101
15.2.1. How the JSON Interface Works	101
15.2.2. Using the JSON Interface from Client Applications	103
15.2.3. How Parameters Are Interpreted	105
15.2.4. Interpreting the JSON Results	106
15.2.5. Error Handling using the JSON Interface	107
15.3. JDBC Interface	108
15.3.1. Using JDBC to Connect to a VoltDB Database	108
15.3.2. Using JDBC to Query a VoltDB Database	108
A. Supported SQL DDL Statements	110
CREATE INDEX	111
CREATE PROCEDURE AS	112

CREATE PROCEDURE FROM CLASS	113
CREATE ROLE	114
CREATE TABLE	115
CREATE VIEW	117
EXPORT TABLE	118
PARTITION PROCEDURE	119
PARTITION TABLE	120
B. Supported SQL Statements	121
DELETE	122
INSERT	123
SELECT	124
UPDATE	128
C. SQL Functions	129
ABS()	131
ARRAY_ELEMENT()	132
ARRAY_LENGTH()	133
AVG()	134
CAST()	135
CEILING()	136
CHAR_LENGTH()	137
CONCAT()	138
COUNT()	139
DECODE()	140
EXP()	141
EXTRACT()	142
FIELD()	144
FLOOR()	146
FROM_UNIXTIME()	147
LEFT()	148
MAX()	149
MIN()	150
OCTET_LENGTH()	151
POSITION()	152
POWER()	153
REPEAT()	154
RIGHT()	155
SINCE_EPOCH()	156
SPACE()	157
SQRT()	158
SUBSTRING()	159
SUM()	160
TO_TIMESTAMP()	161
TRUNCATE()	162
D. VoltDB CLI Commands	163
csvloader	164
dragent	167
exporttofile	168
sqlcmd	171
voltadmin	173
voltdb	175
E. Deployment File (deployment.xml)	179
E.1. Understanding XML Syntax	179
E.2. The Structure of the Deployment File	179
F. System Procedures	183

@AdHoc	184
@Explain	185
@ExplainProc	186
@Pause	187
@Promote	188
@Quiesce	189
@Resume	190
@Shutdown	191
@SnapshotDelete	192
@SnapshotRestore	194
@SnapshotSave	196
@SnapshotScan	199
@SnapshotStatus	202
@Statistics	204
@SystemCatalog	215
@SystemInformation	220
@UpdateApplicationCatalog	222
@UpdateLogging	224

List of Figures

1.1. Partitioning Tables	2
1.2. Serialized Processing	3
1.3. Replicating Tables	4
3.1. Example Reservation Schema	11
10.1. Command Logging in Action	57
10.2. Recovery in Action	58
11.1. K-Safety in Action	63
11.2. Network Partition	67
11.3. Network Fault Protection in Action	69
12.1. The Components of Database Replication	71
12.2. Replicating an Existing Database	72
12.3. Promoting the Replica	72
12.4. Read-Only Access to the Replica	74
13.1. Overview of Export Process	80
13.2. Flight Schema with Export Table	82
13.3. The Components of the Export Process	84
15.1. The Structure of the VoltDB JSON Response	106
E.1. Deployment XML Structure	180

List of Tables

2.1. Operating System and Software Requirements	5
2.2. Components Installed by VoltDB	8
3.1. Example Application Workload	11
3.2. Methods of the VoltTable Classes	19
13.1. File Export Client Properties	86
13.2. JDBC Export Client Properties	87
14.1. VoltDB Components for Logging	95
15.1. Datatypes in the JSON Interface	105
A.1. Supported SQL Datatypes	115
C.1. Selectable Values for the EXTRACT Function	142
E.1. Deployment File Elements and Attributes	180
F.1. @SnapshotSave Options	197

List of Examples

3.1. Components of a VoltDB Stored Procedure	15
3.2. Displaying the Contents of VoltTable Arrays	20

Preface

This book is a complete guide to VoltDB. It describes what VoltDB is, how it works, and — more importantly — how to use it to build high performance, data intensive applications. The book is divided into four sections:

Section 1: Introduction	Explains what VoltDB is, how it works, what problems it solves, and who should use it. The chapters in this section are: <ul style="list-style-type: none">• Chapter 1, <i>Overview</i>• Chapter 2, <i>Installing VoltDB</i>
Section 2: Using VoltDB	Explains how to design and develop applications using VoltDB. The chapters in this section are: <ul style="list-style-type: none">• Chapter 3, <i>Designing Your VoltDB Application</i>• Chapter 4, <i>Simplifying Application Development</i>• Chapter 5, <i>Building Your VoltDB Application</i>• Chapter 6, <i>Running Your VoltDB Application</i>• Chapter 7, <i>Updating Your VoltDB Database</i>
Section 3: Advanced Topics	Provides detailed information about advanced features of VoltDB. Topics covered in this section are: <ul style="list-style-type: none">• Chapter 8, <i>Security</i>• Chapter 9, <i>Saving & Restoring a VoltDB Database</i>• Chapter 10, <i>Command Logging and Recovery</i>• Chapter 11, <i>Availability</i>• Chapter 12, <i>Database Replication</i>• Chapter 13, <i>Exporting Live Data</i>• Chapter 14, <i>Logging and Analyzing Activity in a VoltDB Database</i>• Chapter 15, <i>Using VoltDB with Other Programming Languages</i>
Section 4: Reference Material	Provides reference information about the languages and interfaces used by VoltDB, including: <ul style="list-style-type: none">• Appendix A, <i>Supported SQL DDL Statements</i>• Appendix B, <i>Supported SQL Statements</i>• Appendix C, <i>SQL Functions</i>• Appendix D, <i>VoltDB CLI Commands</i>• Appendix E, <i>Deployment File (deployment.xml)</i>

- | | |
|--|--|
| | • Appendix F, <i>System Procedures</i> |
|--|--|

This book provides the most complete description of the VoltDB product. It includes features from both the open source Community edition and the commercial Enterprise Edition. In general, the features described in Section 2 — chapters 2 through 6 — are available in both versions of the product. Several features in Section 3, advanced topics — such as command logging, database replication, and export to Hadoop and JDBC — are unique to the Enterprise Edition.

If you are new to VoltDB, two companion books, the *VoltDB Tutorial* and *Getting Started with VoltDB*, provide an introduction to the product and its features. These, and other books, are available on the web from <http://www.voltdb.com/>.

Chapter 1. Overview

1.1. What is VoltDB?

VoltDB is a revolutionary new database product. Designed from the ground up to be the best solution for high performance business-critical applications, the VoltDB architecture is able to achieve 45 times higher throughput than current database products. The architecture also allows VoltDB databases to scale easily by adding processors to the cluster as the data volume and transaction requirements grow.

Current commercial database products are designed as general-purpose data management solutions. They can be tweaked for specific application requirements. However, the one-size-fits-all architecture of traditional databases limits the extent to which they can be optimized.

Although the basic architecture of databases has not changed significantly in 30 years, computing has. As have the demands and expectations of business applications and the corporations that depend on them.

VoltDB is designed to take full advantage of the modern computing environment:

- VoltDB uses in-memory storage to maximize throughput, avoiding costly disk access.
- Further performance gains are achieved by serializing all data access, avoiding many of the time-consuming functions of traditional databases such as locking, latching, and maintaining transaction logs.
- Scalability, reliability, and high availability are achieved through clustering and replication across multiple servers and server farms.

VoltDB is a fully ACID-compliant transactional database, relieving the application developer from having to develop code to perform transactions and manage rollbacks within their own application. By using a subset of ANSI standard SQL for the schema definition and data access, VoltDB also reduces the learning curve for experienced database designers.

1.2. Who Should Use VoltDB

VoltDB is not intended to solve all database problems. It is targeted at a specific segment of business computing.

VoltDB focuses specifically on applications that require scalability, reliability, high availability, and outstanding throughput. In other words, VoltDB's target audience is what have traditionally been known as Online Transaction Processing (OLTP) applications. These applications have strict requirements for throughput to avoid bottlenecks. They also have a clearly architected workflow that predefines the allowed data access paths and critical interactions.

VoltDB is used today for traditional high performance applications such as capital markets data feeds, financial trade, telco record streams and sensor-based distribution systems. It's also used in emerging applications like wireless, online gaming, fraud detection, digital ad exchanges and micro transaction systems. Any application requiring high database throughput, linear scaling and uncompromising data accuracy will benefit immediately from VoltDB.

VoltDB is *not* optimized for all types of queries, such as fetching and collating large data sets across multiple tables. This sort of activity is commonly found in business intelligence and data warehousing solutions, for which other database products are better suited.

To aid businesses that require both exceptional transaction performance and ad hoc reporting, VoltDB includes integration functions so that historical data can be exported to an analytic database for larger scale data mining.

1.3. How VoltDB Works

VoltDB is not like traditional database products. There is no such thing as a generic VoltDB "database". Each database is optimized for a specific application by compiling the schema, stored procedures, and partitioning information in to what is known as the VoltDB *application catalog*. The catalog is then loaded on one or more host machines to create the distributed database.

1.3.1. Partitioning

In VoltDB, each stored procedure is defined as a transaction. The stored procedure (i.e. transaction) succeeds or rolls back as a whole, ensuring database consistency.

By analyzing and precompiling the data access logic in the stored procedures, VoltDB can distribute both the data and the processing associated with it to the individual nodes on the cluster. In this way, each node of the cluster contains a unique "slice" of the data and the data processing.

Figure 1.1. Partitioning Tables



1.3.2. Serialized (Single-Threaded) Processing

At run-time, calls to the stored procedures are passed to the appropriate node of the cluster. When procedures are "single-partitioned" (meaning they operate on data within a single partition) the individual node executes the procedure by itself, freeing the rest of the cluster to handle other requests in parallel.

By using serialized processing, VoltDB ensures transactional consistency without the overhead of locking, latching, and transaction logs, while partitioning lets the database handle multiple requests at a time. As a general rule of thumb, the more processors (and therefore the more partitions) in the cluster, the more transactions VoltDB completes per second, providing an easy, almost linear path for scaling an application's capacity and performance.

When a procedure does require data from multiple partitions, one node acts as a coordinator and hands out the necessary work to the other nodes, collects the results and completes the task. This coordination makes multi-partitioned transactions generally slower than single-partitioned transactions. However, transactional integrity is maintained and the architecture of multiple parallel partitions ensures throughput is kept at a maximum.

Figure 1.2. Serialized Processing




It is important to note that the VoltDB architecture is optimized for throughput over latency. The latency of any one transaction (the time from when the transaction begins until processing ends) is similar in VoltDB to other databases. However, the number of transactions that can be completed in a second (i.e. throughput) is orders of magnitude higher because VoltDB reduces the amount of time that requests sit in the queue waiting to be executed. VoltDB achieves this improved throughput by eliminating the overhead required for locking, latching, and other administrative tasks.

1.3.3. Partitioned vs. Replicated Tables

Tables are partitioned in VoltDB based on a primary key that you, the developer or designer, specify. When you choose partitioning keys that match the way the data is accessed by the stored procedures, it optimizes execution at runtime.

To further optimize performance, VoltDB allows certain database tables to be replicated to all partitions of the cluster. For small tables that are largely read-only, this allows stored procedures to create joins between this table and another larger table while remaining a single-partitioned transaction. For example, a retail merchandising database that uses product codes as the primary key may have one table that simply correlates the product code with the product's category and full name. Since this table is relatively small and does not change frequently (unlike inventory and orders) it can be replicated to all partitions. This way stored procedures can retrieve and return user-friendly product information when searching by product code without impacting the performance of order and inventory updates and searches.

Figure 1.3. Replicating Tables

1.3.4. Ease of Scaling to Meet Application Needs

The VoltDB architecture is designed to simplify the process of scaling the database to meet the changing needs of your application. Increasing the number of nodes in a VoltDB cluster both increases throughput (by increasing the number of simultaneous queues in operation) and increases the data capacity (by increasing the number of partitions used for each table).

Scaling up a VoltDB database is a simple process that doesn't require any changes to the database schema or application code. You can either:

- Save the database (using a snapshot or command logging), update the deployment file to identify the number of nodes for the resized cluster, then restart the database using either `restore` or `recover` to reload the data.
- Add nodes "on the fly" while the database is running.

Currently you must restart the database to scale up when using `k-safety` for high availability. However, you can add nodes "on the fly" for databases with `k=0`. This is sometimes referred to as *elastic* scaling. And future releases of VoltDB will support elasticity for all configurations.

Chapter 2. Installing VoltDB

VoltDB is available as both pre-built distributions and as source code. This chapter explains the system requirements, how to install VoltDB, and what resources are provided in the kit.

2.1. Operating System and Software Requirements

The following are the requirements for developing and running VoltDB applications.

Table 2.1. Operating System and Software Requirements

Operating System	<p>VoltDB requires a 64-bit Linux-based operating system. Kits are built and qualified on the following platforms:</p> <ul style="list-style-type: none">• CentOS version 5.8 or later and 6.3 or later• Red Hat (RHEL) version 5.8 or later and 6.3 or later• Ubuntu versions 10.4 and 12.4 <p>Development builds are also available for Macintosh OSX 10.6 and later¹.</p>
CPU	<ul style="list-style-type: none">• Dual core² x86_64 processor• 64 bit• 1.6 GHz
Memory	4 Gbytes ³
Java	Sun JDK 6 update 21 or later
Required Software	<p>NTP⁴</p> <p>Python 2.4 or later release of 2.x</p>
Recommended Software	Eclipse 3.x (or other Java IDE)
<p>Footnotes:</p> <ol style="list-style-type: none">1. CentOS 5.8 and 6.3, RHEL 5.8 and 6.3, and Ubuntu 10.4 and 12.4 are the only officially supported operating systems for VoltDB. However, VoltDB is tested on several other POSIX-compliant and Linux-based 64-bit operating systems, including Macintosh OSX 10.6.2. Dual core processors are a minimum requirement. Four or eight physical cores are recommended for optimal performance.3. Memory requirements are very specific to the storage needs of the application and the number of nodes in the cluster. However, 4 Gigabytes should be considered a minimum configuration.4. NTP minimizes time differences between nodes in a database cluster, which is critical for VoltDB. All nodes of the cluster should be configured to synchronize against the same NTP server. Using a single local NTP server is recommended, but not required.	

2.2. Installing VoltDB

VoltDB is distributed as a compressed tar archive for each of the supported platforms. The best way to install VoltDB is to unpack the distribution kit as a folder in the home directory of your personal account, like so:

```
$ tar -zxvf voltdb-3.5.tar.gz -C $HOME/
```

Installing into your personal directory gives you full access to the software and is most useful for development.

If you are installing VoltDB on a production server where the database will be run, you may want to install the software into a standard system location so that the database cluster can be started with the same commands on all nodes. The following shell commands install the VoltDB software in the folder `/opt/voltdb`:

```
$ sudo tar -zxvf voltdb-3.5.tar.gz -C /opt
$ cd /opt
$ sudo mv voltdb-3.5 voltdb
```

Note that installing as root using the `sudo` command makes the installation folders read-only for non-privileged accounts. Which is why installing in `$HOME` is recommended for running the sample applications and other development activities.

2.2.1. Upgrading an Existing VoltDB Installation

If you are upgrading an existing installation of VoltDB, you have two choices:

- You can unpack the new version as a separate installation. VoltDB does this by default, since the tar file contains the version number in the folder name. Note that if you do install new versions alongside an existing installation, any existing Ant build files or shell scripts you have for building and running VoltDB applications will continue to use the older version.
- You can replace your existing installation with the new version. To do this, you need to delete the folder with your current installation and then follow the instructions for unpacking the new kit. For example, the following shell commands unpack the new version under the user's home directory, delete an old installation, and replace it:

```
$ tar -zxvf voltdb-3.5.tar.gz -C $HOME
$ cd $HOME
$ rm -R voltdb/
$ mv voltdb-3.5 voltdb
```

2.2.2. Performing a System-Wide Installation on Ubuntu

If you plan on using VoltDB on Ubuntu or another Debian-based Linux system, there is a Debian package available to simplify the installation process. Using the Debian package installs VoltDB in the system directories, making VoltDB available to all users of the system without them having to individually configure their `PATH` variable.

To install the Debian package, download the package from the VoltDB web site. Then, from an account with root access issue the following command:

```
$ sudo dpkg -i voltdb_3.5-1_amd64.deb
```

The advantages of using the Debian install package are:

- The installation is completed in a single command. No additional set up is required.
- VoltDB becomes available to all system users.
- Upgrades are written to the same location. You do not need to modify your application scripts or move files after each upgrade.

However, there are a few changes to behavior that you should be aware of if you install VoltDB using the Debian package:

- The VoltDB libraries are installed in `/usr/lib/voltdb`. When compiling stored procedures, you must include this location in your Java classpath.
- The sample applications are installed into the directory `/usr/share/voltdb/examples/`. Because this is a system directory, users cannot run the samples directly in that location. Instead, first copy the folder containing the sample application you want to run and paste a copy into your home directory structure. Then run the sample from your copy. For example:

```
$ cp -r /usr/share/voltdb/examples/voter ~/
$ cd ~/voter
$ ./run.sh
```

2.2.3. Building a New VoltDB Distribution Kit

If you want to build the VoltDB software from source (for example, if you want to test recent development changes), you must first fetch the VoltDB source files. The VoltDB sources are stored in a GitHub repository accessible from the VoltDB community web site.

The VoltDB sources are designed to build and run on 64-bit Linux-based or 64-bit Macintosh platforms. However, the build process has not been tested on all possible configurations. Attempts to build the sources on other operating systems may require changes to the build files and possibly to the sources as well.

Once you obtain the sources, use Ant 1.7 or later to build a new distribution kit for the current platform:

```
$ ant dist
```

The resulting distribution kit is created as `obj/release/volt-n.n.nn.tar.gz` where *n.n.nn* identifies the current version and build numbers. Use this file to install VoltDB according to the instructions in Section 2.2, “Installing VoltDB”.

2.3. Setting Up Your Environment

VoltDB comes with shell command scripts that simplify the process of developing and deploying VoltDB applications. These scripts are in the `/bin` folder under the installation root and define short-cut commands for executing many VoltDB actions. To make the commands available to your session, you must include the `/bin` directory as part your `PATH` environment variable.

You can add the `/bin` directory to your `PATH` variable by redefining `PATH`. For example, the following shell command adds `/bin` to the end of the environment `PATH`, assuming you installed VoltDB as `/voltdb-n.n` in your `$HOME` directory:

```
$ export PATH="$PATH:$HOME/voltdb-n.n/bin"
```

To avoid having to redefine `PATH` every time you create a new session, you can add the preceding command to your shell login script. For example, if you are using the bash shell, you would add the preceding command to the `$HOME/.bashrc` file.

2.4. What is Included in the VoltDB Distribution

Table 2.2 lists the components that are provided as part of the VoltDB distribution.

Table 2.2. Components Installed by VoltDB

Component	Description
VoltDB Software & Runtime	The VoltDB software comes as Java archives (.JAR files) and a callable library that can be found in the <code>/voltdb</code> subfolder. Other software libraries that VoltDB depends on are included in a separate <code>/lib</code> subfolder.
Example Applications	VoltDB comes with several example applications that demonstrate VoltDB capabilities and performance. They can be found in the <code>/examples</code> subfolder.
Demo Dashboard	The demo dashboard provides a quick and easy way to become familiar with VoltDB. The dashboard helps you start, view, and interact with the example applications. Start the dashboard by invoking the <code>Click Here to Start.html</code> file in the top level installation folder.
VoltDB Web Studio	Web Studio is a browser-based tool for visualizing and querying a running VoltDB database that is bundled with the VoltDB server software. You can start Web Studio by connecting to the HTTP port of a running VoltDB database server. For example, <code>http://voltsvr:8080/studio</code> . Note that the httpd server and JSON interface must be enabled to access Web Studio from the server.
Shell Commands	The <code>/bin</code> subfolder contains executable scripts to perform common VoltDB tasks, such as compiling application catalogs and starting the VoltDB server. Add the <code>/bin</code> subfolder to your PATH environment variable to use the following shell commands: <pre>csvloader sqlcmd voltadmin voltdb</pre>
Documentation	Online documentation, including the full manuals and javadoc describing the Java programming interface, is available in the <code>/doc</code> subfolder.

2.5. VoltDB in Action: Running the Sample Applications

Once you install VoltDB, you can use the sample applications to see VoltDB in action and get a better understanding of how it works. The easiest way to do this is to use the Demo Dashboard, which walks you through two of the samples. Open the file named `Click Here to Start.html` in the top level VoltDB folder to start the dashboard.

See the README file in the `/examples` subfolder for a complete list of the applications and brief instructions. The accompanying book *Getting Started with VoltDB* provides more detail about running the example applications and using them to learn how VoltDB works.

Getting Started also contains a tutorial, Hello World, that walks you through the process of writing a VoltDB application from scratch. The sources for the Hello World tutorial are also included in the `/doc/tutorials` subfolder.

Chapter 3. Designing Your VoltDB Application

VoltDB produces ACID-compliant, relational databases using a subset of ANSI-standard SQL for defining the schema and accessing the data. So designing a VoltDB application is very much like designing any other database application.

The difference is that VoltDB requires you to be more organized and planful in your design:

- All data access should be done through stored procedures. Although ad hoc queries are possible, they do not take advantage of the optimizations that make VoltDB's exceptional performance possible.
- The schema and workflow should be designed to promote single-partitioned procedures wherever possible.

These are not unreasonable requirements for high-performance applications. In fact, for 20 years or more OLTP application designers have used these design principles to get the most out of commercial database products. The difference is that VoltDB actually takes advantage of these principles to provide exponentially better throughput without sacrificing any of the value of a fully-transactional database.

The following sections provide guidelines for designing VoltDB applications.

3.1. Designing the Database

VoltDB is a relational database product. Relational databases consist of tables and columns, with constraints, index keys, and aggregated views. VoltDB also uses standard SQL database definition language (DDL) statements to specify the database schema. So designing the schema for a VoltDB database uses the same skills and knowledge as designing a database for Oracle, MySQL, or any other relational database product.

For example, let's assume you are designing a flight reservation system. At its simplest, the application requires database tables for the flights, the customers, and the reservations. Your database schema might look like the following:



Figure 3.1 shows how the schema looks as defined in standard SQL DDL.

Figure 3.1. Example Reservation Schema

```

CREATE TABLE Flight (
    FlightID INTEGER UNIQUE NOT NULL,
    DepartTime TIMESTAMP NOT NULL,
    Origin VARCHAR(3) NOT NULL,
    Destination VARCHAR(3) NOT NULL,
    NumberOfSeats INTEGER NOT NULL,
    PRIMARY KEY(FlightID)
);

CREATE TABLE Reservation (
    ReserveID INTEGER UNIQUE NOT NULL,
    FlightID INTEGER NOT NULL,
    CustomerID INTEGER NOT NULL,
    Seat VARCHAR(5) DEFAULT NULL,
    Confirmed TINYINT DEFAULT '0',
    PRIMARY KEY(ReserveID)
);

CREATE TABLE Customer (
    CustomerID INTEGER UNIQUE NOT NULL,
    FirstName VARCHAR(15),
    LastName VARCHAR (15),
    PRIMARY KEY(CustomerID)
);

```

But a schema is not all you need to define the database (or the application) effectively. You also need to know the expected volume and workload. For our example, let's assume that we expect the following volume of data at any given time:

- Flights: 2,000
- Reservations: 200,000
- Customers: 1,000,000

We can also define a set of functions the application must perform and the expected frequency. Again, for the sake of our example, let's assume the following is the estimated workload.

Table 3.1. Example Application Workload

Use Case	Frequency
Look up a flight (by origin and destination)	10,000/sec
See if a flight is available	5,000/sec
Make a reservation	1,000/sec
Cancel a reservation	200/sec
Look up a reservation (by reservation ID)	200/sec
Look up a reservation (by customer ID)	100/sec
Update flight info	1/sec
Take off (close reservations and archive associated records)	1/sec

This additional information about the volume and workload affects the design of both the database and the application, because it impacts what SQL queries need to be written and what keys to use for accessing the data.

In the case of VoltDB, you use this additional information to configure the database and optimize performance. Specifically, you want to partition the individual tables to ensure that the most frequent transactions are single-partitioned.

The following sections discuss how to partition a database to maximize throughput, using the flight reservation case study as an example.

3.1.1. Partitioning Database Tables

The goal of partitioning the database tables is to ensure that the most frequent transactions are single-partitioned. This is particularly important for queries that modify the data, such as INSERT, UPDATE, and DELETE statements.

Looking at the workload for the reservation system, the key transactions to focus on are looking up a flight, seeing if a flight is available (in other words, has sufficient space), looking up a reservation, and making a reservation. Of these transactions, only the last modifies the database.

3.1.1.1. Choosing a Partition Column

We will discuss the Flight table later. But first let's look at the Reservation table. Reservation has a primary key, ReserveID, which is a unique identifier for the reservation. Looking at the schema alone, ReserveID might look like a good column to use to partition the table.

However, looking at the workload, there are only two transactions that are keyed to the reservation ID (looking up a reservation by ID and canceling a reservation), which occur only 200 times a second. Whereas, seeing if a flight has available seats, which requires looking up reservations by the Flight ID, occurs 5,000 times a second, or 25 times as frequently. Therefore, the Reservation table needs to be partitioned on the FlightID column.

Moving to the Customer table, it also has a unique identifier, CustomerID. Although customers might need to look up their record by name, the first and last names are not guaranteed to be unique and so CustomerID is used for most data access. Therefore, CustomerID is the best column to use for partitioning the Customer table.

Once you choose the columns to use for partitioning your database tables, you can define your partitioning choices in the database schema. Specifying the partitioning along with the schema DDL helps keep all of the database structural information in one place.

You define the partitioning scheme using the PARTITION TABLE statement, specifying the partitioning column for each table. For example, to specify FlightID and CustomerID as the partitioning columns for the Reservation and Customer tables, respectively, your database schema must include the following statements:

```
PARTITION TABLE Reservation ON COLUMN FlightID;  
PARTITION TABLE Customer ON COLUMN CustomerID;
```

3.1.1.2. Rules for Partitioning Tables

The following are the rules to keep in mind when choosing a column by which to partition a table:

- **Any integer or string column can be a partition column.** VoltDB can partition on any column that is an integer (TINYINT, SMALLINT, INTEGER, or BIGINT) or string (VARCHAR) datatype.

- **There is only one partition column per table.** If you need to partition a table on two columns (for example first and last name), add an additional column (fullname) that combines the values of the two columns and use this new column to partition the table.
- **Partition columns do not need to have unique values, but they cannot be null.** Numeric fields can be zero and string or character fields can be empty, but the column cannot contain a null value. You must specify NOT NULL in the schema, or VoltDB will report it as an error when you compile the schema.

3.1.2. Replicating Tables

The previous section describes how to choose a partitioning column for database tables, using the Reservation and Customer tables as examples. But what about the Flight table? It is possible to partition the Flight table (for example, on the FlightID column). However, not all tables benefit from partitioning.

Small, mostly read-only tables can be replicated across all of the partitions of a VoltDB database. This is particularly useful when a table is not accessed by a single column primarily.

3.1.2.1. Choosing Replicated Tables

Looking at the workload of the flight reservation example, the Flight table has the most frequent accesses (at 10,000 a second). However, these transactions are read-only and may involve any combination of three columns: the point of origin, the destination, and the departure time. Because of the nature of this transaction, it makes it hard to partition the table in a way that would make it single-partitioned.

Fortunately, the number of flights available for booking at any given time is limited (estimated at 2,000) and so the size of the table is relatively small (approximately 36 megabytes). In addition, all of the transactions involving the Flight table are read-only except when new flights are added and at take off (when the records are deleted). Therefore, Flight is a good candidate for replication.

Note that the Customer table is also largely read-only. However, because of the volume of data in the Customer table (a million records), it is not a good candidate for replication, which is why it is partitioned.

3.1.2.2. Specifying Replicated Tables

In VoltDB, you do not explicitly state that a table is replicated. If you do not specify a partitioning column in the database schema, the table will by default be replicated.

So, in our flight reservation example, there is no explicit action required to replicate the Flight table. However, it is very important to specify partitioning information for tables that you want to partition. If not, they will be replicated by default, significantly changing the performance characteristics of your application.

3.2. Designing the Data Access (Stored Procedures)

As you can see from the previous discussion of designing the database, defining the database schema — and particularly the partitioning plan — goes hand in hand with understanding how the data is accessed. The two must be coordinated to ensure optimum performance.

It doesn't matter whether you design the partitioning first or the data access first, as long as in the end they work together. However, for the sake of example, we will use the schema and partitioning outlined in the preceding sections when discussing how to design the data access.

3.2.1. Writing VoltDB Stored Procedures

The key to designing the data access for VoltDB applications is that complex or performance sensitive access to the database should be done through stored procedures. It is possible to perform ad hoc queries on a VoltDB database. However, ad hoc queries do not benefit as fully from the performance optimizations VoltDB specializes in and therefore should not be used for frequent, repetitive, or complex transactions.

In VoltDB, a stored procedure and a transaction are one and the same. The stored procedure succeeds or rolls back as a whole. Also, because the transaction is defined in advance as a stored procedure, there is no need for specific `BEGIN TRANSACTION` or `END TRANSACTION` commands.¹

Within the stored procedure, you access the database using standard SQL syntax, with statements such as `SELECT`, `UPDATE`, `INSERT`, and `DELETE`. You can also include your own code within the stored procedure to perform calculations on the returned values, to evaluate and execute conditional statements, or to perform any other functions your applications need.

3.2.2. VoltDB Stored Procedures and Determinism

To ensure data consistency and durability, VoltDB procedures must be *deterministic*. That is, given specific input values, the outcome of the procedure is predictable. Determinism is critical because it allows the same stored procedure to run in multiple locations and give the same results. It is determinism that makes it possible to run redundant copies of the database partitions without impacting performance. (See Chapter 11, *Availability* for more information on redundancy and availability.)

One key to deterministic behavior is avoiding ambiguous SQL queries. Specifically, performing unsorted queries can result in a nondeterministic outcome. VoltDB does not guarantee a consistent order of results unless you use a tree index to scan the records in a specific order or you specify an `ORDER BY` clause in the query itself. In the worst case, a limiting query, such as `SELECT TOP 10 Emp_ID FROM Employees` without an index or `ORDER BY` clause, can result in a different set of rows being returned. However, even a simple query such as `SELECT * from Employees` can return the same rows in a different order.

The problem is that even when these queries are read-only, VoltDB may detect inconsistency in the results of the stored procedure. For clusters with a K-safety value greater than zero, this means unsorted query results returned by two copies of the same partition may not match, a condition that VoltDB detects and reports as corruption. It is possible one or more nodes of the cluster may crash in this situation. Consequently, when returning multiple rows, use of an `ORDER BY` clause or a tree index in a `WHERE` constraint is strongly recommended for all `SELECT` statements.

Another key to deterministic behavior is avoiding external functions or procedures that can introduce arbitrary data. External functions include file and network I/O (which should be avoided any way because they can impact latency), as well as many common system-specific procedures such as `Date` and `Time`.

However, this limitation does not mean you cannot use arbitrary data in VoltDB stored procedures. It just means you must either generate the arbitrary data outside the stored procedure and pass it in as input parameters or generate it in a deterministic way.

For example, if you need to load a set of records from a file, you can open the file in your application and pass each row of data to a stored procedure that loads the data into the VoltDB database. This is the best method when retrieving arbitrary data from sources (such as files or network resources) that would impact latency.

The other alternative is to use data that can be generated deterministically. For two of the most common cases, timestamps and random values, VoltDB provides a method for doing this:

¹One side effect of transactions being precompiled as stored procedures is that external transaction management frameworks, such as Spring or JEE, are not supported by VoltDB.

- `VoltProcedure.getTransactionTime()` returns a timestamp that can be used in place of the Java `Date` or `Time` classes.
- `VoltProcedure.getSeededRandomNumberGenerator()` returns a pseudo random number that can be used in place of the Java `Util.Random` class.

These procedures use the current transaction ID to generate a deterministic value for the timestamp and the random number.

Finally, even seemingly harmless programming techniques, such as static variables can introduce unpredictable behavior. VoltDB provides no guarantees concerning the state of the stored procedure class instance across invocations. Any information that you want to persist across invocations must either be stored in the database itself or passed into the stored procedure as a procedure parameter.

3.2.3. The Anatomy of a VoltDB Stored Procedure

The stored procedures themselves are written as Java classes, each procedure being a separate class. Example 3.1, “Components of a VoltDB Stored Procedure” shows the stored procedure that looks up a flight to see if there are any available seats. The callouts identify the key components of a VoltDB stored procedure.

Example 3.1. Components of a VoltDB Stored Procedure

```
package fadvisor.procedures;

import org.voltdb.*; ❶

public class HowManySeats extends VoltProcedure { ❷

    public final SQLStmt GetSeatCount = new SQLStmt( ❸
        "SELECT NumberOfSeats, COUNT(ReserveID) " +
        "FROM Flight AS F, Reservation AS R " +
        "WHERE F.FlightID=R.FlightID AND R.FlightID=? " +
        "GROUP BY NumberOfSeats;");

    public long run( int flightid)
        throws VoltAbortException { ❹

        long numofseats;
        long seatsinuse;
        VoltTable[] queryresults;

        voltQueueSQL( GetSeatCount, flightid); ❺
        queryresults = voltExecuteSQL(); ❻

        VoltTable result = queryresults[0]; ❼
        if (result.getRowCount() < 1) { return -1; }
        numofseats = result.fetchRow(0).getLong(0);
        seatsinuse = result.fetchRow(0).getLong(1);

        numofseats = numofseats - seatsinuse; ❽
        return numofseats; // Return available seats
    }
}
```

- ❶ Stored procedures are written as Java classes. To access the VoltDB classes and methods, be sure to import `org.voltodb.*`.
- ❷ Each stored procedure extends the generic class `VoltProcedure`.
- ❸ Within the stored procedure you access the database using a subset of ANSI-standard SQL statements. To do this, you declare the statement as a special Java type called `SQLStmt`. In the SQL statement, you insert a question mark (?) everywhere you want to replace a value by a variable at runtime. (See Appendix B, *Supported SQL Statements* for details on the supported SQL statements.)
- ❹ The bulk of the stored procedure is the `run` method. Note that the `run` method throws the exception `VoltAbortException` if any exceptions are not caught. `VoltAbortException` causes the stored procedure to rollback. (See Section 3.2.3.5, “Rolling Back a Transaction” for more information about rollback.)
- ❺ To perform database queries, you queue SQL statements (specifying both the SQL statement and the variables to use) using the `voltQueueSQL` method.
- ❻ Once you queue all of the SQL statements you want to perform, use `voltExecuteSQL` to execute the statements in the queue.
- ❼ Each statement returns its results in a `VoltTable` structure. Because the queue can contain multiple queries, `voltExecuteSQL` returns an array of `VoltTable` structures, one array element for each query.
- ❽ In addition to queueing and executing queries, stored procedures can contain custom code. Note, however, you should limit the amount of custom code in stored procedures to only that processing that is necessary to complete the transaction, so as not to delay the following transactions in the queue.

The following sections describe these components in more detail.

3.2.3.1. The Structure of the Stored Procedure

VoltDB stored procedures are Java classes. The key points to remember are to:

- Import the VoltDB classes in `org.voltodb.*`
- Include the class definition, which extends the abstract class `VoltProcedure`
- Define the method `run`, that performs the SQL queries and processing that make up the transaction

The following diagram illustrates the basic structure if a VoltDB stored procedure.

```
import org.voltodb.*;

public class Procedure-name extends VoltProcedure {

    // Declare SQL statements ...

    public datatype run ( arguments ) throws VoltAbortException {

        // Body of the Stored Procedure ...

    }
}
```

3.2.3.2. Creating and Executing SQL Queries in Stored Procedures

The main function of the stored procedure is to perform database queries. In VoltDB this is done in two steps:

1. Queue the queries using the `voltQueueSQL` function
2. Execute the queue and return the results using `voltExecuteSQL`

The first argument to `voltQueueSQL` is the SQL statement to be executed. The SQL statement is declared using a special class, `SQLStmt`, with question marks as placeholders for values that will be inserted at runtime. The remaining arguments to `voltQueueSQL` are the actual values that VoltDB inserts into the placeholders.

For example, if you want to perform a `SELECT` of a table using two columns in the `WHERE` clause, your SQL statement might look something like this:

```
SELECT CustomerID FROM Customer WHERE FirstName=? AND LastName=?;
```

At runtime, you want the question marks replaced by values passed in as arguments from the calling application. So the actual `voltQueueSQL` invocation might look like this:

```
public final SQLStmt getcustid = new SQLStmt(
    "SELECT CustomerID FROM Customer " +
    "WHERE FirstName=? AND LastName=?");
...

voltQueueSQL(getcustid, firstnm, lastnm);
```

Once you have queued all of the SQL statements you want to execute together, you can then process the queue using the `voltExecuteSQL` function:

```
VoltTable[] queryresults = voltExecuteSQL();
```

Note that you can queue multiple SQL statements before calling `voltExecuteSQL`. This improves performance when executing multiple SQL queries because it minimizes the amount of network traffic within the cluster.

You can also queue and execute SQL statements as many times as necessary to complete the transaction. For example, if you want to make a flight reservation, you may need to verify that the flight exists before creating the reservation. One way to do this is to look up the flight, verify that a valid row was returned, then insert the reservation, like so:

```
final String getflight = "SELECT FlightID FROM Flight WHERE FlightID=?";
final String makeres = "INSERT INTO Reservation (?, ?, ?, ?, ?, ?)";

public final SQLStmt getflightsql = new SQLStmt(getflight);
public final SQLStmt makeressql = new SQLStmt(makeres);

public VoltTable[] run( int servenum, int flightnum, int customernum )
    throws VoltAbortException {

    // Verify flight exists
    voltQueueSQL(getflightsql, flightnum);
    VoltTable[] queryresults = voltExecuteSQL();

    // If there is no matching record, rollback
    if (queryresults[0].getRowCount() == 0 ) throw new VoltAbortException();
```

```
        // Make reservation
        voltQueueSQL(makeressql, reservnum, flightnum, customernum,0,0);
        return voltExecuteSQL();
    }
```

3.2.3.3. Interpreting the Results of SQL Queries

When you call `voltExecuteSQL`, the results of all the queued SQL statements are returned in an array of `VoltTable` structures. The array contains one `VoltTable` for each SQL statement in the queue. The `VoltTables` are returned in the same order as the respective SQL statements in the queue.

The `VoltTable` itself consists of rows. Each row contains columns. Each column has a label and a value of a fixed datatype. The number of rows and columns per row depends on the specific query.

For example, if you queue two SQL `SELECT` statements, one looking for the destination of a specific flight and the second looking up the `ReserveID` and Customer name (first and last) of reservations for that flight, the code for the stored procedure might look like the following:

```
public final SQLStmt getdestsql = new SQLStmt(
    "SELECT Destination FROM Flight WHERE FlightID=?;");
public final SQLStmt getressql = new SQLStmt(
    "SELECT r.ReserveID, c.FirstName, c.LastName " +
    "FROM Reservation AS r, Customer AS c " +
    "WHERE r.FlightID=? AND r.CustomerID=c.CustomerID;");

...

    voltQueueSQL(getdestsql, flightnum);
    voltQueueSQL(getressql, flightnum);
    VoltTable[] results = voltExecuteSQL();
```

The array returned by `voltExecuteSQL` will have two elements:

- The first array element is a `VoltTable` with one row (`FlightID` is defined as unique) with one column, because the `SELECT` statement returns only one value.
- The second array element is a `VoltTable` with as many rows as there are reservations for the specific flight, each row containing three columns: `ReserveID`, `FirstName`, and `LastName`.

VoltDB provides a set of convenience routines for accessing the contents of the `VoltTable` array. Table 3.2, “Methods of the `VoltTable` Classes” lists some of the most common methods.

Table 3.2. Methods of the VoltTable Classes

Method	Description
<code>int fetchRow(int index)</code>	Returns an instance of the <code>VoltTableRow</code> class for the row specified by index.
<code>int getRowCount()</code>	Returns the number of rows in the table.
<code>int getColumnCount()</code>	Returns the number of columns for each row in the table.
<code>Type getColumnType(int index)</code>	<p>Returns the datatype of the column at the specified index. Type is an enumerated type with the following possible values:</p> <p>BIGINT DECIMAL FLOAT INTEGER INVALID NULL NUMERIC SMALLINT STRING TIMESTAMP TINYINT VARBINARY VOLTTABLE</p>
<code>String getColumnName(int index)</code>	Returns the name of the column at the specified index.
<code>double getDouble(int index)</code> <code>long getLong(int index)</code> <code>String getString(int index)</code> <code>BigDecimal getDecimalAsBigDecimal(int index)</code> <code>double getDecimalAsDouble(int index)</code> <code>Date getTimestampAsTimestamp(int index)</code> <code>long getTimestampAsLong(int index)</code> <code>byte[] getVarbinary(int index)</code>	<p>Methods of <code>VoltTable.Row</code></p> <p>Return the value of the column at the specified index in the appropriate datatype. Because the datatype of the columns vary depending on the SQL query, there is no generic method for returning the value. You must specify what datatype to use when fetching the value.</p>

It is also possible to retrieve the column values by name. You can invoke the `getDatatype` methods passing a string argument specifying the name of the column, rather than the numeric index.

Accessing the columns by name can make code easier to read and less susceptible to errors due to changes in the SQL schema (such as changing the order of the columns). On the other hand, accessing column values by numeric index is potentially more efficient under heavy load conditions.

Example 3.2, “Displaying the Contents of VoltTable Arrays” shows a generic routine for walking through the return results of a stored procedure. In this example, the contents of the VoltTable array are written to standard output.

Example 3.2. Displaying the Contents of VoltTable Arrays

```
public void displayResults(VoltTable[] results) {
    int table = 1;
    for (VoltTable result : results) {
        System.out.printf("*** Table %d ***\n",table++);
        displayTable(result);
    }
}

public void displayTable(VoltTable t) {

    final int colCount = t.getColumnCount();
    int rowCount = 1;
    t.resetRowPosition();
    while (t.advanceRow()) {
        System.out.printf("--- Row %d ---\n",rowCount++);

        for (int col=0; col<colCount; col++) {
            System.out.printf("%s: ",t.columnName(col));
            switch(t.getColumnType(col)) {
                case TINYINT: case SMALLINT: case BIGINT: case INTEGER:
                    System.out.printf("%d\n", t.getLong(col));
                    break;
                case STRING:
                    System.out.printf("%s\n", t.getString(col));
                    break;
                case DECIMAL:
                    System.out.printf("%f\n", t.getDecimalAsBigDecimal(col));
                    break;
                case FLOAT:
                    System.out.printf("%f\n", t.getDouble(col));
                    break;
            }
        }
        rowCount++;
    }
}
```

For further details on interpreting the VoltTable structure, see the Java documentation that is provided online in the doc/ subfolder for your VoltDB installation.

3.2.3.4. Returning Results from a Stored Procedure

Stored procedures can return a single VoltTable, an array of VoltTables, or a long integer. You can return all of the query results by returning the VoltTable array, or you can return a scalar value that is the logical result of the transaction. (For example, the stored procedure in Example 3.1, “Components of a VoltDB Stored Procedure” returns a long integer representing the number of remaining seats available in the flight.)

Whatever value the stored procedure returns, make sure the run method includes the appropriate datatype in its definition. For example, the following two definitions specify different return datatypes; the first returns a long integer and the second returns the results of a SQL query as a VoltTable array.

```
public long run( int flightid)

public VoltTable[] run ( String lastname, String firstname)
```


It is important to note that you can interpret the results of SQL queries either in the stored procedure or in the client application. However, for performance reasons, it is best to limit the amount of additional processing done by the stored procedure to ensure it executes quickly and frees the queue for the next stored procedure. So unless the processing is necessary for subsequent SQL queries, it is usually best to return the query results (in other words, the VoltTable array) directly to the calling application and interpret them there.

3.2.3.5. Rolling Back a Transaction

Finally, if a problem arises while a stored procedure is executing, whether the problem is anticipated or unexpected, it is important that the transaction rolls back. Rollback means that any changes made during the transaction are undone and the database is left in the same state it was in before the transaction started.

VoltDB is a fully transactional database, which means that if a transaction (i.e. stored procedure) fails, the transaction is automatically rolled back and the appropriate exception is returned to the calling application. Exceptions that can cause a rollback include the following:

- Runtime errors in the stored procedure code, such as division by zero or datatype overflow.
- Violating database constraints in SQL queries, such as inserting a duplicate value into a column defined as unique.

There may also be situations where a logical exception occurs. In other words, there is no programmatic issue that might be caught by Java or VoltDB, but a situation occurs where there is no practical way for the transaction to complete. In these conditions, the stored procedure can force a rollback by explicitly throwing the VoltAbortException exception.

For example, if a flight ID does not exist, you do not want to create a reservation so the stored procedure can force a rollback like so:

```
if (!flightid) { throw new VoltAbortException(); }
```

See Section 4.3, “Verifying Expected Query Results” for another way to roll back procedures when queries do not meet necessary conditions.

3.2.4. Partitioning Stored Procedures

To make your stored procedures accessible in the database, you must declare them in the DDL schema using the CREATE PROCEDURE statement. For example, the following statements declare five stored procedures, identifying them by their class name:

```
CREATE PROCEDURE FROM CLASS procedures.LookupFlight;  
CREATE PROCEDURE FROM CLASS procedures.HowManySeats;  
CREATE PROCEDURE FROM CLASS procedures.MakeReservation;  
CREATE PROCEDURE FROM CLASS procedures.CancelReservation;  
CREATE PROCEDURE FROM CLASS procedures.RemoveFlight;
```

You can also declare your stored procedures as single-partitioned or not. If you do not declare a procedure as single-partitioned, it is assumed to be multi-partitioned by default.

The advantage of multi-partitioned stored procedures is that they have full access to all of the data in the database. However, the real focus of VoltDB, and the way to achieve maximum throughput for your OLTP application, is through the use of single-partitioned stored procedures.

Single-partitioned stored procedures are special because they operate independently of other partitions (which is why they are so fast). At the same time, single-partitioned stored procedures operate on only a

subset of the entire data (i.e. only the data within the specified partition). Most important of all *it is the responsibility of the application developer to ensure that the SQL queries within the stored procedure are actually single-partitioned.*

When you declare a stored procedure as single-partitioned, you must specify both the partitioning table and column using the PARTITION PROCEDURE statement in the schema DDL. For example, in our sample application the table RESERVATION is partitioned on FLIGHTID. Let's say you create a stored procedure with two arguments, *flight_id* and *reservation_id*. You declare the stored procedure as single-partitioned in the DDL schema using the FLIGHTID column as the partitioning column. By default, the first parameter to the procedure, *flight_id*, is used as the hash value. For example:

```
PARTITION PROCEDURE MakeReservation ON TABLE Reservation COLUMN FlightID;
```

At this point, your stored procedure can operate on only those records in the RESERVATION with FLIGHTID=*flight_id*. What's more it can only operate on records in other partitioned tables *that are partitioned on the same hash value.*

In other words, the following rules apply:

- Any SELECT, UPDATE, or DELETE queries of the RESERVATION table must use the constraint WHERE FLIGHTID=? (where the question mark is replaced by the value of *flight_id*).
- SELECT statements can join the RESERVATION table to replicated tables, as long as the preceding constraint is also applied.
- SELECT statements can join the RESERVATION table to other partitioned tables as long as the following is true:
 - The two tables are partitioned on the same column (in this case, FLIGHTID).
 - The tables are joined on the shared partitioning column.
 - The preceding constraint (WHERE RESERVATION.FLIGHTID=?) is used.

For example, the RESERVATION table can be joined to the FLIGHT table (which is replicated). However, the RESERVATION table *cannot* be joined with the CUSTOMER table in a single-partitioned stored procedure because the two tables use different partitioning columns. (CUSTOMER is partitioned on the CUSTOMERID column.)

The following are examples of invalid SQL queries for a single-partitioned stored procedure partitioned on FLIGHTID:

- INVALID: `SELECT * FROM reservation WHERE reservationid=?`
- INVALID: `SELECT c.lastname FROM reservation AS r, customer AS c WHERE r.flightid=? AND c.customerid = r.customerid`

In the first example, the RESERVATION table is being constrained by a column (RESERVATIONID) which is *not* the partitioning column. In the second example, the correct partitioning column is being used in the WHERE clause, but the tables are being joined on a different column. As a result, not all CUSTOMER rows are available to the stored procedure since the CUSTOMER table is partitioned on a different column than RESERVATION.

Warning

It is the application developer's responsibility to ensure that the queries in a single-partitioned stored procedure are truly single-partitioned. VoltDB *does not* warn you about SELECT or

DELETE statements that will return incomplete results. VoltDB does generate a runtime error if you attempt to INSERT a row that does not belong in the current partition.

Finally, the PARTITION PROCEDURE statement assumes that the partitioning column value is the first parameter to the procedure. If you wish to partition on a different parameter value, say the third parameter, you must specify the partitioning parameter using the PARAMETER clause and a zero-based index for the parameter position. In other words, the index for the third parameter would be "2" and the PARTITION PROCEDURE statement would read as follows:

```
PARTITION PROCEDURE GetCustomerDetails
  ON TABLE Customer COLUMN CustomerID
  PARAMETER 2;
```

3.3. Designing the Application Logic

Once you design your database schema, partitioning, and stored procedures, you are ready to write the application logic. Most of the logic and code of the calling programs are specific to the application you are designing. The important aspect, with regards to using VoltDB, is understanding how to:

- Create a connection to the database
- Call stored procedures
- Close the client connection

The following sections explain how to perform these functions using the standard VoltDB Java client interface. The VoltDB Java client is a thread-safe class library that provides runtime access to VoltDB databases and functions.

It is possible to call VoltDB stored procedures from programming languages other than Java. However, reading this chapter is still recommended to understand the process for invoking and interpreting the results of a VoltDB stored procedure. See Chapter 15, *Using VoltDB with Other Programming Languages* for more information about using VoltDB from applications written in other languages.

3.3.1. Connecting to the VoltDB Database

The first step for the calling program is to create a connection to the VoltDB database. You do this by:

1. Defining the configuration for your connections
2. Creating an instance of the VoltDB Client class
3. Calling the createConnection method

```
org.voltdb.client.Client client = null;
ClientConfig config = null;
try {
    config = new ClientConfig("advent","xyzy");
    client = ClientFactory.createClient(config);
    client.createConnection("myserver.xyz.net");
} catch (java.io.IOException e) {
    e.printStackTrace();
    System.exit(-1);
}
```

In its simplest form, the `ClientConfig` class specifies the username and password to use. It is not absolutely necessary to create a client configuration object. For example, if security is not enabled (and therefore a username and password are not needed) a configuration object is not required. But it is a good practice to define the client configuration to ensure the same credentials are used for all connections against a single client. It is also possible to define additional characteristics of the client connections as part of the configuration, such as the timeout period for procedure invocations or a status listener. (See Section 3.4, “Handling Errors” for details.)

Once you instantiate your client object, the argument to `createConnection` specifies the database node to connect to. You can specify the server node as a hostname (as in the preceding example) or as an IP address. You can also add a second argument if you want to connect to a port other than the default. For example, the following `createConnection` call attempts to connect to the admin port, 21211:

```
client.createConnection("myserver.xyz.net", 21211);
```

If security is enabled and the username and password in the `ClientConfig` do not match a user defined in the deployment file, the call to `createConnection` will throw an exception. See Chapter 8, *Security* for more information about the use of security with VoltDB databases.

You can create the connection to any of the nodes in the database cluster and your stored procedure will be routed appropriately. In fact, you can create connections to multiple nodes on the server and your subsequent requests will be distributed to the various connections.

Creating multiple connections has little effect when you are making synchronous requests. However, for asynchronous requests, multiple connections can help balance the load across the cluster.

When you are done with the connection, you should make sure your application calls the `close` method to clean up any memory allocated for the connection.

```
try {
    client.close();
} catch (InterruptedException e) {
    e.printStackTrace();
}
```

3.3.2. Invoking Stored Procedures

Once you create the connection, you are ready to call the stored procedures. You invoke a stored procedure using the `callProcedure` method, passing the procedure name and variables as arguments to `callProcedure`. For example, to invoke the `LookupFlight` stored procedure that requires three values (the originating airport, the destination, and the departure time), the call to `callProcedure` might look like this:

```
VoltTable[] results;
try { results = client.callProcedure("LookupFlight",
                                    origin,
                                    dest,
                                    departtime).getResults();
} catch (Exception e) {
    e.printStackTrace();
    System.exit(-1);
}
```

Note that since `callProcedure` can throw an exception (such as `VoltAbortException`) it is a good practice to perform error handling and catch known exceptions.

Once a synchronous call completes, you can evaluate the results of the stored procedure. The `callProcedure` method returns a `ClientResponse` object, which includes information about the success or failure of the stored procedure. To retrieve the actual return values you use the `getResults()` method, as in the preceding example. See Section 3.2.3.3, “Interpreting the Results of SQL Queries” for more information about interpreting the results of VoltDB stored procedures.

3.3.3. Invoking Stored Procedures Asynchronously

Calling stored procedures synchronously can be useful because it simplifies the program logic; your client application waits for the procedure to complete before continuing. However, for high performance applications looking to maximize throughput, it is better to queue stored procedure invocations asynchronously.

To invoke stored procedures asynchronously, you use the `callProcedure` method with an additional argument, a callback that will be notified when the procedure completes (or an error occurs). For example, to invoke a procedure to add a new customer asynchronously, the call to `callProcedure` might look like the following:

```
client.callProcedure(new MyCallback(), `
                        "NewCustomer",
                        firstname,
                        lastname,
                        custID`);
```

The callback procedure (`MyCallback` in this example) is invoked once the stored procedure completes. It is passed the same structure, `ClientResponse`, that is returned by a synchronous invocation. `ClientResponse` contains information about the results of execution. In particular, the methods `getStatus` and `getResults` let your callback procedure determine whether the stored procedure was successful and evaluate the results of the procedure.

The following is an example of a callback procedure:

```
static class MyCallback implements ProcedureCallback {
    @Override
    public void clientCallback(ClientResponse clientResponse) {

        if (clientResponse.getStatus() != ClientResponse.SUCCESS) {
            System.err.println(clientResponse.getStatusString());
        } else {
            myEvaluateResultsProc(clientResponse.getResults());
        }
    }
}
```

Several important points to note about making asynchronous invocations of stored procedures:

- Asynchronous calls to `callProcedure` return control to the calling application as soon as the procedure call is queued.
- If the database server queue is full, `callProcedure` will block until it is able to queue the procedure call. This is a condition known as *backpressure*. This situation does not normally happen unless the database cluster is not scaled sufficiently for the workload or there are abnormal spikes in the workload. Two ways to handle this situation programmatically are to:
 - Let the client pause momentarily to let the queue subside. The asynchronous client interface does this automatically for you.

- Create multiple connections to the cluster to better distribute asynchronous calls across the database nodes.
- Once the procedure is queued, any subsequent errors (such as an exception in the stored procedure itself or loss of connection to the database) are returned as error conditions to the callback procedure.

3.3.4. Closing the Connection

When the client application is done interacting with the VoltDB database, it is a good practice to close the connection. This ensures that any pending transactions are completed in an orderly way. There are two steps to closing the connection:

1. Call `drain()` to make sure all asynchronous calls have completed.
2. Call `close()` to close all of the connections and release any resources associated with the client.

The `drain()` method pauses the current thread until all outstanding asynchronous calls (and their callback procedures) complete. This call is not necessary if the application only makes synchronous procedure calls. However, there is no penalty for calling `drain()` and so it can be included for completeness in all applications.

The following example demonstrates how to close the client connection:

```
try {
    client.drain();
    client.close();
} catch (InterruptedException e) {
    e.printStackTrace();
}
```

3.4. Handling Errors

One special situation to consider when calling VoltDB stored procedures is error handling. The VoltDB client interface catches most exceptions, including connection errors, errors thrown by the stored procedures themselves, and even exceptions that occur in asynchronous callbacks. These error conditions are not returned to the client application as exceptions. However, the application can still receive notification and interpret these conditions using the client interface.

The following sections explain how to identify and interpret errors that occur executing stored procedures and in asynchronous callbacks.

3.4.1. Interpreting Execution Errors

If an error occurs in a stored procedure (such as an SQL constraint violation), VoltDB catches the error and returns information about it to the calling application as part of the `ClientResponse` class.

The `ClientResponse` class provides several methods to help the calling application determine whether the stored procedure completed successfully and, if not, what caused the failure. The two most important methods are `getStatus()` and `getStatusString()`.

The `getStatus()` method tells you whether the stored procedure completed successfully and, if not, what type of error occurred. The possible values of `getStatus()` are:

- **CONNECTION_LOST** — The network connection was lost before the stored procedure returned status information to the calling application. The stored procedure may or may not have completed successfully.
- **CONNECTION_TIMEOUT** — The stored procedure took too long to return to the calling application. The stored procedure may or may not have completed successfully. See Section 3.4.2, “Handling Time-outs” for more information about handling this condition.
- **GRACEFUL_FAILURE** — An error occurred and the stored procedure was gracefully rolled back.
- **RESPONSE_UNKNOWN** — This is a rare error that occurs if the coordinating node for the transaction fails before returning a response. The node to which your application is connected cannot determine if the transaction failed or succeeded before the coordinator was lost. The best course of action, if you receive this error, is to use a new query to determine if the transaction failed or succeeded and then take action based on that knowledge.
- **SUCCESS** — The stored procedure completed successfully.
- **UNEXPECTED_FAILURE** — An unexpected error occurred on the server and the procedure failed.
- **USER_ABORT** — The code of the stored procedure intentionally threw a `UserAbort` exception and the stored procedure was rolled back.

It is good practice to always check the status of the `ClientResponse` before evaluating the results of a procedure call, because if the status is anything but **SUCCESS**, there will not be any results returned. In addition to identifying the type of error, for any values other than **SUCCESS**, the `getStatusString()` method returns a text message providing more information about the specific error that occurred.

If your stored procedure wants to provide additional information to the calling application, there are two more methods to the `ClientResponse` that you can use. The methods `getAppStatus()` and `getAppStatusString()` act like `getStatus()` and `getStatusString()`, but rather than returning information set by VoltDB, `getAppStatus()` and `getAppStatusString()` return information set by the stored procedure code itself.

In the stored procedure, you can use the methods `setAppStatusCode()` and `setAppStatusString()` to set the values returned to the calling application. For example:

Stored Procedure

```
final byte AppCodeWarm = 1;
final byte AppCodeFuzzy = 2;
. . .
setAppStatusCode(AppCodeFuzzy);
setAppStatusString("I'm not sure about that...");
. . .
```

Client Application

```
static class MyCallback implements ProcedureCallback {
    @Override
    public void clientCallback(ClientResponse clientResponse) {
        final byte AppCodeWarm = 1;
        final byte AppCodeFuzzy = 2;

        if (clientResponse.getStatus() != ClientResponse.SUCCESS) {
            System.err.println(clientResponse.getStatusString());
        } else {
```

```

        if (clientResponse.getAppStatus() == AppCodeFuzzy) {
            System.err.println(clientResponse.getAppStatusString());
        };
        myEvaluateResultsProc(clientResponse.getResults());
    }
}
}

```

3.4.2. Handling Timeouts

One particular error that needs special handling is if a connection or a stored procedure call times out. By default, the client interface only waits a specified amount of time (two minutes) for a stored procedure to complete. If no response is received from the server before the timeout period expires, the client interface returns control to your application, notifying it of the error. For synchronous procedure calls, the client interface returns the error `CONNECTION_TIMEOUT` to the procedure call. For asynchronous calls, the client interface invokes the callback including the error information in the `clientResponse` object.

Similarly, if no response of any kind is returned on a connection (even if no transactions are pending) within the specified timeout period, the client connection will timeout. When this happens, the connection is closed, any open stored procedures on that connection are closed with a return status of `CONNECTION_LOST`, then the client status listener callback method `connectionLost` is invoked. Unlike a procedure timeout, when the connection times out, the connection no longer exists, so your client application will receive no further notifications concerning pending procedures, whether they succeed or fail.

It is important to note that `CONNECTION_TIMEOUT` does not necessarily mean the procedure failed. In fact, it is very possible that the procedure may complete and return information after the timeout error is reported. The timeout is provided to avoid locking up the client application when procedures are delayed or the connection to the cluster hangs for any reason.

Similarly, `CONNECTION_LOST` does not necessarily mean a pending procedure failed. It is possible that the procedure completed but was unable to return its status due to a connection failure. The goal of the connection timeout is to notify the client application of a lost connection in a timely manner, even if there is no outstanding procedures using the connection.

There are several things you can do to address potential timeouts in your application:

- Change the timeout period by calling either or both the methods `setProcedureCallTimeout` and `setConnectionResponseTimeout` on the `ClientConfig` object. The default timeout period is 2 minutes for both procedures and connections. Specify the timeout in milliseconds, although the actual timeouts will only be accurate to within approximately a second of the specified value. Set the value to zero to disable timeouts. For example, the following client code resets the procedure timeout to 90 seconds and the connection timeout period to 3 minutes, or 180 seconds:

```

config = new ClientConfig("advent", "xyzyzy");
config.setProcedureCallTimeout(90 * 1000);
config.setConnectionResponseTimeout(180 * 1000);
client = ClientFactory.createClient(config);

```

- Catch and respond to the timeout error as part of the response to a procedure call. For example, the following code excerpt from a client callback procedure reports the error to the console and ends the callback:

```

static class MyCallback implements ProcedureCallback {
    @Override
    public void clientCallback(ClientResponse response) {

```



```
if (response.getStatus() == ClientResponse.CONNECTION_TIMEOUT) {  
    System.out.println("A procedure invocation has timed out.");  
    return;  
};  
if (response.getStatus() == ClientResponse.CONNECTION_LOST) {  
    System.out.println("Connection lost before procedure response.");  
    return;  
};
```

- Set a status listener to receive the results of any procedure invocations that complete after the client interface times out. See the following section, Section 3.4.3, “Interpreting Other Errors”, for an example of creating a status listener for delayed procedure responses.

3.4.3. Interpreting Other Errors

Certain types of errors can occur that the `ClientResponse` class cannot notify you about immediately. These errors include:

Backpressure

If backpressure causes the client interface to wait, the stored procedure is never queued and so your application does not receive control until after the backpressure is removed. This can happen if the client applications are queuing stored procedures faster than the database cluster can process them. The result is that the execution queue on the server gets filled up and the client interface will not let your application queue any more procedure calls.

Lost Connection

If a connection to the database cluster is lost or times out and there are outstanding asynchronous requests on that connection, the `ClientResponse` for those procedure calls will indicate that the connection failed before a return status was received. This means that the procedures may or may not have completed successfully. If no requests were outstanding, your application might not be notified of the failure under normal conditions, since there are no callbacks to identify the failure. Since the loss of a connection can impact the throughput or durability of your application, it is important to have a mechanism for general notification of lost connections outside of the procedure callbacks.

Exceptions in a Procedure Callback

An error can occur in an asynchronous callback after the stored procedure completes. These exceptions are also trapped by the VoltDB client, but occur after the `ClientResponse` is returned to the application.

Delayed Procedure Responses

Procedure invocations that time out in the client may later complete on the server and return results. Since the client application can no longer react to this response inline (for example, with asynchronous procedure calls, the associated callback has already received a connection timeout error) the client may want a way to process the returned results.

In each of these cases, an error happens and is caught by the client interface outside of the normal stored procedure execution cycle. If you want your application to address these situations, you need to create a listener, which is a special type of asynchronous callback, that the client interface will notify whenever such errors occur.

You must define the listener before you define the VoltDB client or open a connection. The `ClientStatusListenerExt` interface has four methods that you can implement — one for each type of error situation — *connectionLost*, *backpressure*, *uncaughtException*, and *lateProcedureResponse*. Once you declare your `ClientStatusListenerExt`, you add it to a `ClientConfig` object that is then used to define the client. The configuration class also defines the username and password to use for all connections.

By performing the operations in this order, you ensure that all connections to the VoltDB database cluster use the same credentials for authentication and will notify the status listener of any error conditions outside of normal procedure execution.

The following example illustrates:

- ❶ Declaring a `ClientStatusListenerExt`
- ❷ Defining the client configuration, including authentication credentials and the status listener
- ❸ Creating a client with the specified configuration

For the sake of example, this status listener does little more than display a message on standard output. However, in real world applications the listener would take appropriate actions based on the circumstances.

```
/*
 * Declare the status listener
 */
ClientStatusListenerExt mylistener = new ClientStatusListenerExt() ❶
{
    @Override
    public void connectionLost(String hostname, int port,
                               int connectionsLeft,
                               DisconnectCause cause)
    {
        System.out.printf("A connection to the database been lost. "
            + "There are %d connections remaining.\n", connectionsLeft);
    }

    @Override
    public void backpressure(boolean status)
    {
        System.out.println("Backpressure from the database "
            + "is causing a delay in processing requests.");
    }

    @Override
    public void uncaughtException(ProcedureCallback callback,
                                   ClientResponse r, Throwable e)
    {
        System.out.println("An error has occurred in a callback "
            + "procedure. Check the following stack trace for details.");
        e.printStackTrace();
    }

    @Override
    public void lateProcedureResponse(ClientResponse response,
                                       String hostname, int port)
    {
        System.out.printf("A procedure that timed out on host %s:%d"
```

```
        + " has now responded.\n", hostname, port);
    }
};

/*
 * Declare the client configuration, specifying
 * a username, a password, and the status listener
 */
ClientConfig myconfig = new ClientConfig("username",      ❷
                                         "password",
                                         mylistener);

/*
 * Create the client using the specified configuration.
 */
Client myclient = ClientFactory.createClient(myconfig);  ❸
```

Chapter 4. Simplifying Application Development

The previous chapter (Chapter 3, *Designing Your VoltDB Application*) explains how to develop your VoltDB database application using the full power and flexibility of the Java client interface. However, some database tasks — such as inserting records into a table or retrieving a specific column value — do not need all of the capabilities that the Java API provides.

Now that you know how the VoltDB programming interface works, VoltDB has features to simplify common tasks and make your application development easier. Those features include:

1. Default procedures for partitioned tables
2. Shortcuts for defining simple stored procedures
3. Verifying expected SQL query results

The following sections describe each of these features separately.

4.1. Default Procedures for Partitioned Tables

Although it is possible to define quite complex SQL queries, often the simplest are also the most common. Inserting, selecting, updating, and deleting records based on a specific key value are the most basic operations for a database.

To simplify these operations, VoltDB defines default stored procedures to perform these queries for any partitioned table where the partitioning column is part of the primary key index. When you compile the application catalog, these default procedures are added to the catalog automatically.

The default stored procedures use a standard naming scheme, where the name of the procedure is composed of the name of the table (in all uppercase), a period, and the name of the query in lowercase. The parameters to the procedures differ based on the procedure. For the insert procedure, the parameters are the columns of the table, in the same order as defined in the schema. For the select and delete procedures, only the primary key column values are required (listed in the order they appear in the primary key definition). For the update procedure, the columns are the new column values, in the order defined by the schema, followed by the primary key column values. (This means the primary key column values are specified twice, once as their corresponding new column values and once as the primary key value.)

For example, the Hello World tutorial contains a single table, `HELLOWORLD`, with three columns and the partitioning column, `DIALECT`, as the primary key. As a result, the application catalog includes four default stored procedures, in addition to any user-defined procedures declared in the schema. Those default procedures are:

- `HELLOWORLD.insert`
- `HELLOWORLD.select`
- `HELLOWORLD.update`
- `HELLOWORLD.delete`

The following code example uses the default procedures for the `HELLOWORLD` table to insert, retrieve, update, and delete a new record with the key value "American":

```
VoltTable[] results;  
client.callProcedure("HELLOWORLD.insert",  
    "American", "Howdy", "Earth");  
results = client.callProcedure("HELLOWORLD.select",  
    "American").getResults();  
client.callProcedure("HELLOWORLD.update",  
    "American", "Yo", "Biosphere",  
    "American");  
client.callProcedure("HELLOWORLD.delete",  
    "American");
```

4.2. Shortcut for Defining Simple Stored Procedures

Sometimes all you want is to execute a single SQL query and return the results to the calling application. In these simple cases, writing the necessary Java code can be tedious. So VoltDB provides a shortcut.

For very simple stored procedures that execute a single SQL query and return the results, you can define the entire stored procedure as part of the database schema. Normally, the schema contains entries that identify each of the stored procedures, like so:

```
CREATE PROCEDURE FROM CLASS procedures.MakeReservation;  
CREATE PROCEDURE FROM CLASS procedures.CancelReservation;
```

The CREATE PROCEDURE statement specifies the class name of the Java procedure you write. However, to create procedures without writing any Java, you can simply insert the SQL query in the AS clause:

```
CREATE PROCEDURE procedures.simple.CountReservations AS  
    SELECT COUNT(*) FROM RESERVATION;
```

When you include the SQL query in the CREATE PROCEDURE AS statement, VoltDB generates the necessary Java code for you and compiles it when you build your application (as described in Section 5.3, “Building the Application Catalog”). Note that you must still provide a unique class name for the procedure. It is a good idea to put these simplified procedures into a separate package (*procedures.simple*, in the preceding example) from those written by hand.

It is also possible to pass arguments to the SQL query in simple stored procedures. If you use the question mark placeholder in the SQL, any additional arguments you pass through the callProcedure method are used to replace the placeholders, in their respective order. For example, the following simple stored procedure expects to receive three additional parameters:

```
CREATE PROCEDURE procedures.simple.MyReservationsByTrip AS  
    SELECT R.RESERVEID, F.FLIGHTID, F.DEPARTTIME  
    FROM RESERVATION AS R, FLIGHT AS F  
    WHERE R.CUSTOMERID = ?  
    AND R.FLIGHTID = F.FLIGHTID  
    AND F.ORIGIN=? AND F.DESTINATION=?;
```

Finally, you can also specify whether the simple procedure is single-partitioned or not. By default, simple stored procedures are assumed to be multi-partitioned. But if your procedure is single-partitioned, you can specify the partitioning information in a PARTITION PROCEDURE statement. In the following example, the stored procedure is partitioned on the FLIGHTID column of the RESERVATION table using the first parameter as the partitioning key.

```
CREATE PROCEDURE procedures.simple.FetchReservations AS
  SELECT * FROM RESERVATION WHERE FLIGHTID=?;
PARTITION PROCEDURE procedures.simple.FetchReservations
ON TABLE Reservation COLUMN flightid;
```

4.3. Verifying Expected Query Results

The automated default and simple stored procedures reduce the coding needed to perform simple queries. However, another substantial chunk of stored procedure and application code is often required to verify the correctness of the results returned by the queries. Did you get the right number of records? Does the query return the correct value?

Rather than you having to write the code to validate the query results manually, VoltDB provides a way to perform several common validations as part of the query itself. The Java client interface includes an Expectation object that you can use to define the expected results of a query. Then, if the query does not meet those expectations, the stored procedure throws a `VoltAbortException` and rolls back.

You specify the expectation as the second parameter (after the SQL statement but before any arguments) when queuing the query. For example, when making a reservation in the Flight application, the procedure must make sure there are seats available. To do this, the procedure must determine how many seats the flight has. This query can also be used to verify that the flight itself exists, because there should be one and only one record for every flight ID.

The following code fragment uses the `EXPECT_ONE_ROW` expectation to both fetch the number of seats and verify that the flight itself exists and is unique.

```
import org.voltadb.Expectation;
.
.
.
public final SQLStmt GetSeats = new SQLStmt(
    "SELECT numberofseats FROM Flight WHERE flightid=?");

voltQueueSQL(GetSeats, EXPECT_ONE_ROW, flightid);
VoltTable[] recordset = voltExecutesQL();
Long numofseats = recordset[0].asScalarLong();
```

By using the expectation, the stored procedure code does not need to do additional error checking to verify that there is one and only one row in the result set. The following table describes all of the expectations that are available to stored procedures.

Expectation	Description
<code>EXPECT_EMPTY</code>	The query must return no rows.
<code>EXPECT_ONE_ROW</code>	The query must return one and only one row.
<code>EXPECT_ZERO_OR_ONE_ROW</code>	The query must return no more than one row.
<code>EXPECT_NON_EMPTY</code>	The query must return at least one row.
<code>EXPECT_SCALAR</code>	The query must return a single value (that is, one row with one column).
<code>EXPECT_SCALAR_LONG</code>	The query must return a single value with a datatype of Long.
<code>EXPECT_SCALAR_MATCH(long)</code>	The query must return a single value equal to the specified Long value.

Chapter 5. Building Your VoltDB Application

Once you have designed your application and created the source files, you are ready to build your application. There are four steps to building a VoltDB application:

1. Compiling the client application and stored procedures
2. Declaring the stored procedures in the schema
3. Compiling the VoltDB application catalog

This chapter explains these steps in more detail.

5.1. Compiling the Client Application and Stored Procedures

The VoltDB client application and stored procedures are written as Java classes¹, so you compile them using the Java compiler. To do this, you must include the VoltDB libraries in the classpath so Java can resolve references to the VoltDB classes and methods. It is possible to do this manually by defining the environment variable CLASSPATH or using the `-classpath` argument on the command line, like so:

```
$ javac -classpath " ./:/opt/voltdb/voltdb/*" *.java
```

The preceding example assumes that the VoltDB software has been installed in the folder `/opt/voltdb`. If you installed VoltDB in a different directory, you will need to include your installation path in the `-classpath` argument. Also, if your client application depends on other libraries, they will need to be included in the classpath as well.

5.2. Declaring the Stored Procedures

In addition to compiling the stored procedures, you must tell VoltDB which procedures to include in the runtime catalog. You do this by adding `CREATE PROCEDURE` statements to the database schema. For example:

```
CREATE PROCEDURE FROM CLASS procedures.LookupFlight;  
CREATE PROCEDURE FROM CLASS procedures.HowManySeats;  
CREATE PROCEDURE FROM CLASS procedures.MakeReservation;  
CREATE PROCEDURE FROM CLASS procedures.CancelReservation;  
CREATE PROCEDURE FROM CLASS procedures.RemoveFlight;
```

Be sure to identify all of your stored procedures or they will not be included in the catalog and therefore will not be available to the client applications at runtime.

You also specify the partitioning of the database tables and stored procedures in the schema. The important point is that if you do not specify partitioning information for a table, that table will be replicated in all

¹Although VoltDB stored procedures must be written in Java and the primary client interface is Java, it is possible to write client applications using other programming languages. See Chapter 15, *Using VoltDB with Other Programming Languages* for more information on alternate client interfaces.

partitions. See Section 3.1, “Designing the Database” for more information about partitioned and replicated tables.

5.3. Building the Application Catalog

You build the application catalog for your VoltDB database by compiling the database schema and stored procedures into the catalog. To run the compiler, use the **voltadb compile** command, specifying three arguments:

1. The path to your compiled stored procedure classes
2. The name of the schema file to use as input
3. The name of the application catalog to create as output

For example, if your stored procedure classes are in a subfolder called `obj`, the command might be:

```
$ voltadb compile --classpath="obj" -o flight.jar flightschema.sql
```

If you do not specify an output file, the catalog is created as `catalog.jar` in the current working directory.

Chapter 6. Running Your VoltDB Application

There are three steps to running a VoltDB application:

- Defining the cluster configuration
- Starting the VoltDB database
- Starting the client application or applications

The following sections describe the procedures for starting and stopping a VoltDB database in detail.

6.1. Defining the Cluster Configuration

The schema that is used to compile the application catalog defines how the database is logically structured: what tables to create, which tables are partitioned, and how they are accessed (i.e. what stored procedures to support). The other important aspect of a running database is the physical layout of the cluster that runs the database. This includes information such as:

- The number of nodes in the cluster
- The number of partitions (or "sites") per node
- The amount of K-safety to establish for durability

You define the cluster configuration in the *deployment file*. The deployment file is an XML file, which you specify when you start the database to establish the correct cluster topology. The basic syntax of the deployment file is as follows:

```
<?xml version="1.0"?>
<deployment>
  <cluster hostcount="n"
           sitesperhost="n"
           kfactor="n"
  />
</deployment>
```

The attributes of the `<cluster>` tag define the physical layout of the hardware that will run the database. Those attributes are:

- **hostcount** — specifies the number of nodes in the cluster.
- **sitesperhost** — specifies the number of partitions (or "sites") per host. In general, this value is related to the number of processor cores per node. Section 6.1.1, "Determining How Many Partitions to Use" explains how to choose a value for this attribute,
- **kfactor** — specifies the K-safety value to use when creating the database. This attribute is optional. If you do not specify a value, it defaults to zero. (See Chapter 11, *Availability* for more information about K-safety.)

In the simplest case — when running on a single node with no special options enabled — you can skip the deployment file altogether and specify only the catalog on the command line. If you do not specify

a deployment file or host, VoltDB defaults to one node, two sites per host, a K-safety value of zero, and localhost as the host.

The deployment file is used to enable and configure many other runtime options related to the database, which are described later in this book. For example, the deployment file specifies whether security is enabled and defines the users and passwords that are used to authenticate clients at runtime. See Chapter 8, *Security* for more information about security and VoltDB databases.

6.1.1. Determining How Many Partitions to Use

In general, the number of partitions per node is related to the number of processor cores each system has, the optimal number being approximately 3/4 of the number of CPUs reported by the operating system. For example, if you are using a cluster of dual quad-core processors (in other words, 8 cores per node), the optimal number of partitions is likely to be 6 or 7 partitions per node.

For systems that support hyperthreading (where the number of physical cores support twice as many threads), the operating system reports twice the number of physical cores. In other words, a dual quad-core system would report 16 virtual CPUs. However, each partition is not quite as efficient as on non-hyperthreading systems. So the optimal number of partitions is more likely to be between 10 and 12 per node in this situation.

Because there are no hard and set rules, the optimal number of partitions per node is best calculated by actually benchmarking the application to see what combination of cores and partitions produces the best results. However, two important points to keep in mind are:

- It is never useful to specify more partitions than the number of CPUs reported by the operating system.
- All nodes in the cluster will use the same number of partitions, so the best performance is achieved by using a cluster with all nodes having the same physical architecture (i.e. cores).

6.1.2. Configuring Paths for Runtime Features

In addition to configuring the database process on each node of the cluster, the deployment file lets you enable and configure a number of features within VoltDB. Export, automatic snapshots, and network partition detection are all enabled through the deployment file. The later chapters of this book describe these features in detail.

An important aspect of these features is that some of them make use of disk resources for persistent storage across sessions. For example, automatic snapshots need a directory for storing snapshots of the database contents. Similarly, export uses disk storage for writing overflow data if the export client cannot keep up with the export queue.

You can specify individual paths for each feature, or you can specify a root directory where VoltDB will create subfolders for each feature as needed. To specify a common root, use the `<voltdbroot>` tag (as a child of `<paths>`) to specify where VoltDB will store disk files. For example, the following `<paths>` tag set specifies `/tmp` as the root directory:

```
<paths>
  <voltdbroot path="/tmp" />
</paths>
```

Of course, `/tmp` is appropriate for temporary files, such as export overflow. But `/tmp` is not a good location for files that must persist when the server reboots. So you can also identify specific locations for individual features. For example, the following excerpt from a deployment file specifies `/tmp` as the default root but `/opt/voltdbsaves` as the directory for automatic snapshots:

```
<paths>
  <voltdbroot path="/tmp" />
  <snapshots path="/opt/voltdbsaves" />
</paths>
```

If you specify a root directory path, the directory must exist and the process running VoltDB must have write access to it. VoltDB does not attempt to create an explicitly named root directory path if it does not exist.

On the other hand, if you do not specify a root path or a specific feature path, the root path defaults to `./voltdbroot` in the current default directory and VoltDB creates the directory (and subfolders) as needed. Similarly, if you name a specific feature path (such as the snapshots path) and it does not exist, VoltDB will attempt to create it for you.

6.1.3. Verifying your Hardware Configuration

The deployment file defines the expected configuration of your database cluster. However, there are several important aspects of the physical hardware and operating system configuration that you should be aware of before running VoltDB:

- VoltDB can operate on heterogeneous clusters. However, best performance is achieved by running the cluster on similar hardware with the same type of processors, number of processors, and amount of memory on each node.
- All nodes must be able to resolve the IP addresses and host names of the other nodes in the cluster. That means they must all have valid DNS entries or have the appropriate entries in their local hosts file.
- You must run NTP on all of the cluster nodes, preferably synchronizing against the same local time server. If the time skew between nodes in the cluster is greater than 100 milliseconds, VoltDB cannot start the database.
- It is strongly recommended that you run NTP with the `-x` argument. Using `ntpd -x` stops the server from adjusting time backwards for all but very large increments. If the server time moves backward, VoltDB must pause and wait for time to catch up.

6.2. Starting a VoltDB Database for the First Time

Once you define the configuration of your cluster, you start a VoltDB database by starting the VoltDB server process on each node of the cluster. You start the server process by invoking VoltDB and specifying:

- A startup action (see Section 6.5, “Stopping and Restarting a VoltDB Database” for details)
- The hostname or IP address of the host node in the cluster
- The location of the application catalog
- The location of the deployment file

The *host* can be any node in the cluster and plays a special role during startup; it hosts the application catalog and manages the cluster initiation process. Once startup is complete, the host's role is complete and it becomes a peer of all the other nodes. It is important that all nodes in the cluster can resolve the hostname or IP address of the host node you specify.

For example, the following `voltdb` command starts the cluster with the **create** startup action, specifying the location of the catalog and the deployment files, and naming `voltsvr1` as the host node:

```
$ voltdb create \  
    host voltsvr1 \  
    catalog mycatalog.jar \  
    deployment deployment.xml
```

If you are using the VoltDB Enterprise Edition, you must also specify the location of the license file. The license file is only required by the host node when starting the cluster; the license argument is ignored in all other cases (including when using the community edition). This way, you can use the same command on all nodes.

The command to start a cluster using the Enterprise Edition looks like this:

```
$ voltdb create \  
    host voltsvr1 \  
    catalog mycatalog.jar \  
    deployment deployment.xml \  
    license /opt/voltdb/voltdb/license.xml
```

When you are developing an application (where your cluster consists of a single node using localhost), this one command is sufficient to start the database. However, when starting a cluster, you must:

1. Copy the runtime catalog to the host node.
2. Copy the deployment file to all nodes of the cluster.
3. Log in and start the server process using the preceding command on each node.

The deployment file must be identical on all nodes for the cluster to start.

6.2.1. Simplifying Startup on a Cluster

Manually logging on to each node of the cluster every time you want to start the database can be tedious. There are several ways you can simplify the startup process:

- **Shared network drive** — By creating a network drive and mounting it (using NFS) on all nodes of the cluster, you can distribute the runtime catalog and deployment file (and the VoltDB software) by copying it once to a single location.
- **Remote access** — When starting the database, you can specify the location of either the runtime catalog or the deployment file as a URL rather than a file path (for example, `http://myserver.com/mycatalog.jar`). This way you can publish the catalog and deployment file once to a web server and start all nodes of the server from those copies.
- **Remote shell scripts** — Rather than manually logging on to each cluster node, you can use secure shell (ssh) to execute shell commands remotely. By creating an ssh script (with the appropriate permissions) you can copy the files and/or start the database on each node in the cluster from a single script.
- **VoltDB Enterprise Manager** — The VoltDB Enterprise Edition includes a web-based management console, called the VoltDB Enterprise Manager, that helps you manage the configuration, initialization, and performance monitoring of VoltDB databases. The Enterprise Manager automates the startup process for you. See the *VoltDB Management Guide* for details.

6.2.2. How VoltDB Database Startup Works

When you are starting a VoltDB database, the VoltDB server process performs the following actions:

1. If you are starting the database on the node identified as the host node, it waits for initialization messages from the remaining nodes.
2. If you are starting the database on a non-host node, it sends an initialization message to the host indicating that it is ready.
3. Once all the nodes have sent initialization messages, the host sends out a message to the other nodes that the cluster is complete. The host then distributes the application catalog to all nodes.

At this point, the cluster is complete and the database is ready to receive requests from client applications. Several points to note:

- Once the startup procedure is complete, the host's role is over and it becomes a peer like every other node in the cluster. It performs no further special functions.
- The database is not operational until the correct number of nodes (as specified in the deployment file) have connected.

6.3. Starting VoltDB Client Applications

Client applications written in Java compile and run like other Java applications. Once again, when you start your client application, you must make sure that the VoltDB library JAR file is in the classpath. For example:

```
$ java -classpath ".:/opt/voltdb/voltdb/*" MyClientApp
```

When developing your application (using one of the sample applications as a template), the `run.sh` file manages this dependency for you. However, if you are running the database on a cluster and the client applications on separate machines, you do not need to include all of the VoltDB software with your client application.

The VoltDB distribution comes with two separate libraries: `voltdb-n.n.nn.jar` and `voltdbclient-n.n.nn.jar` (where *n.n.nn* is the VoltDB version number). The first file is a complete library that is required for building and running a VoltDB database server. The second file, `voltdbclient-n.n.nn.jar`, is a smaller library containing only those components needed to run a client application.

If you are distributing your client applications, you only need to distribute the client classes and the VoltDB client library. You do not need to install all of the VoltDB software distribution on the client nodes.

6.4. Shutting Down a VoltDB Database

Once the VoltDB database is up and running, you can shut it down by stopping the VoltDB server processes on each cluster node. However, it is easier to stop the database as a whole with a single command. You can do this either programmatically with the `@Shutdown` system procedure or interactively with the **`voltadmin shutdown`** command.

Either calling the `@Shutdown` system procedure (from any node) or invoking **`voltadmin shutdown`** will shutdown the database on the entire cluster. You do not have to issue commands on each node. Entering **`voltadmin shutdown`** without specifying a host server assumes the current system is part of the database

cluster. To shutdown a database running on different servers, you use the `--host`, `--user`, and `--password` arguments to access the remote database. For example, the following command shuts down the VoltDB database that includes the server `zeus`:

```
$ voltadmin --host=zeus shutdown
```

6.5. Stopping and Restarting a VoltDB Database

Because VoltDB is an in-memory database, once the database server process stops, the data itself is removed from memory. If you restart the database without taking any other action, the database starts fresh without any data. However, in many cases you want to retain the data across sessions. There are two ways to do this:

- Save and restore database snapshots
- Use command logging and recovery to reload the database automatically

6.5.1. Save and Restore

A database *snapshot* is exactly what it sounds like — a point-in-time copy the database contents written to disk. You can later use the snapshot to restore the data.

To save and restore data across sessions, you can perform a snapshot before shutting down the database and then restore the snapshot after the database restarts. You can perform a manual snapshot using the **voltadmin** command or using the `@SnapshotSave` system procedure. For example, the following commands pause the database, perform a manual snapshot, then do a shutdown on the current system:

```
$ voltadmin pause
$ voltadmin save 'voltdbroot/snapshots' 'MySnapshot'
$ voltdbadmin shutdown
```

You can also have the database automatically create periodic snapshots using the snapshot feature in the deployment file. See Chapter 9, *Saving & Restoring a VoltDB Database* for more information about using snapshots to save and restore the database.

6.5.2. Command Logging and Recovery

Another option for saving data across sessions is to use command logging and recovery. When you enable command logging, the database not only performs periodic snapshots, it also keeps a log of all stored procedures that are initiated at each partition. If the database stops for any reason — either intentionally or due to system failure — when the server process restarts, the database restores the last snapshot and then "replays" the command log to recover all of the data committed prior to the cluster shutting down.

To support command logging, an alternative startup action is available on the command line when starting the server process. The valid startup actions are:

- **create** — explicitly creates a new, empty database and ignores any command log information, if it exists.
- **recover** — starts a new database process and recovers the command log from the last database session. The `recover` action is explicit; if the command log content is not found or is incomplete, the server initialization process stops and reports an error.

Even if you are not using command logging, you can still use the `create` and `recover` actions with automated snapshots. During the `recover` action, VoltDB attempts to restore the last snapshot found in the snapshot paths. Therefore, using automated snapshots and the `recover` action, it is possible to automatically recover all of the data from the previous database session up until the last snapshot.

The following example illustrates how to recover a database from a previous session.

```
$ voltdb recover \  
    host voltsvr1 \  
    catalog mycatalog.jar \  
    deployment deployment.xml \  
    license /opt/voltdb/voltdb/license.xml
```

The advantages of command logging and recovery are that:

- The command log ensures that all data is recovered, including transactions between snapshots.
- The recovery is automated, ensuring no client activity occurs until the recovery is complete.

See Chapter 10, *Command Logging and Recovery* for more information about enabling and configuring command logging.

6.6. Modes of Operation

There are actually two modes of operation for a VoltDB database: normal operation and admin mode. During normal operation clients can connect to the cluster and invoke stored procedures (as allowed by the security permissions set in the application catalog and deployment files). In *admin mode*, only clients connected through a special admin port are allowed to initiate stored procedures. Requests received from any other clients are rejected.

6.6.1. Admin Mode

The goal of admin mode is to quell database activity prior to executing sensitive administrative functions. By entering admin mode, it is possible to ensure that no changes are made to the database contents during operations such as save, restore, or updating the runtime catalog.

You initiate admin mode by calling the `@Pause` system procedure through the admin port. The *admin port* works just like the regular client port and can be called through any of the standard VoltDB client interfaces (such as Java or JSON) by specifying the admin port number when you create the client connection.

Once the database enters admin mode, any requests received over the client port are rejected, returning a status of `ClientResponse.SERVER_UNAVAILABLE`. The client application can check for this response and resubmit the transaction after a suitable pause.

By default the admin port is 21211, but you can specify an alternate admin port using the `<admin-mode>` tag in the deployment file. For example:

```
<deployment>  
    ...  
    <admin-mode port="9999" />  
</deployment>
```

Once admin mode is turned on, VoltDB processes requests received over the admin port only. Once you are ready to resume normal operation, you must call the system procedure `@Resume` through the admin port.

6.6.2. Starting the Database in Admin Mode

By default, a VoltDB database starts in normal operating mode. However, you can tell the database to start in admin mode by adding the `adminstartup` attribute to the `<admin-mode>` tag in the deployment file. For example:

```
<deployment>
...
  <admin-mode port="9999" adminstartup="true" />
</deployment>
```

When `adminstartup` is set to `true`, the database starts in admin mode. No activity is allowed over the standard client port until you explicitly stop admin mode with the **`voltadmin resume`** command or a call to the `@Resume` system procedure.

Starting in admin mode can be very useful, especially if you want to perform some initialization on the database prior to allowing client access. For example, it is recommended that you start in admin mode if you plan to manually restore a snapshot or prepopulate the database with data through a set of custom stored procedures. For example, the following commands restore a snapshot, then exit admin mode once the initialization is complete:

```
$ voltadmin restore 'voltdbroot/snapshots' 'MySnapshot'
$ voltdbadmin resume
```

Chapter 7. Updating Your VoltDB Database

Unlike traditional databases that allow interactive SQL statements for defining and modifying database tables, VoltDB requires you to pre-compile the schema and stored procedures into the application catalog. Pre-compiling lets VoltDB verify the structure of the database (including the partitioning) and optimize the stored procedures for maximum performance.

The down side of pre-compiling the database and stored procedures is that you cannot modify the database as easily as you can with more traditional relational database products. Of course, this constraint is both a blessing and a curse. It helps you avoid making rash or undocumented changes to the database without considering the consequences.

It is never a good idea to change the database structure or stored procedure logic arbitrarily. But VoltDB recognizes the need to make adjustments even on running systems. Therefore, the product provides mechanisms for updating your database and hardware configuration as needed, while still providing the structure and verification necessary to maintain optimal performance.

7.1. Planning Your Application Updates

Many small changes to the database application, such as bug fixes to the internal code of a stored procedure or adding a table to the database schema, do not have repercussions on other components of the system. It is nice to be able to make these changes with a minimal amount of disruption. Other changes can impact multiple aspects of your applications. For example if you add or remove an index from a table or modify the parameters to a stored procedure. Therefore, it is important to think through the consequences of any changes you make.

VoltDB tries to balance the trade offs of changing the database environment, making simple changes easy and automating as much as possible even complex changes. Using the VoltDB Enterprise Edition you can add, remove, or update stored procedures "on the fly", while the database is running. You can also add or drop tables and columns from the schema, as well as modify many indexes.

To make other changes to the database schema (such as adding unique indexes) you must first save and shutdown the database. However, even in this situation, VoltDB automates the process by transforming the data when you restart and reload the database in a new configuration.

This chapter explains different methods for making changes to your VoltDB database application, including:

- Updating the Database Schema on a Running Database
- Updating the Database Using Save and Restore
- Updating the Hardware Configuration

7.2. Updating the Database Schema on a Running Database

Note

This section describes the use of the **voltadmin update** command and @UpdateApplicationCatalog stored procedure, features that are available in the VoltDB Enterprise Edition. If you are

using the community edition, use the save and restore process described in Section 7.3, “Updating the Database Using Save and Restore” to update your database.

Many normal changes to the database schema and stored procedures can be made "on the fly", in other words while the database is running. These changes include:

- Adding, removing, or updating tables, columns, and indexes
- Adding or removing materialized views and export-only tables
- Adding, removing, or updating stored procedures and the security permissions for accessing them

Live schema updates are done by creating an updated application catalog and deployment file and telling the database process to use the new catalog. You do this with the `@UpdateApplicationCatalog` system procedure, or from the shell prompt using the **voltadmin update** command. The process is as follows:

1. Make the necessary changes to the source code for the stored procedures and the schema.
2. Recompile the class files and the application catalog as described in Chapter 5, *Building Your VoltDB Application*.
3. Use the `@UpdateApplicationCatalog` system procedure or **voltadmin update** command to pass the new catalog and deployment file to the cluster.

For example:

```
$ voltdb compile -o mycatalog.jar myschema.sql
$ voltadmin update mycatalog.jar mydeployment.xml
```

7.2.1. Validating the Updated Catalog

When you submit a catalog update, the database nodes do a comparison of the new catalog and deployment configuration with the currently running catalog to ensure that only supported changes are included. If unsupported changes are included, the command returns an error.

Most schema changes are supported. The only changes that are not currently allowed are changes that add constraints to an existing index or column or that make changes to the contents of an existing view. To make these more complex changes, you need to save and restore the database to change the catalog, as described in Section 7.3, “Updating the Database Using Save and Restore”.

7.2.2. Managing the Update Process

Updating the application catalog lets you modify the database schema and its stored procedures without disrupting the normal operations. However, even when a change is allowed, you should be careful of the impact to client applications that use those procedures. For example, if you remove a table or change the parameters to a stored procedure while client applications are still active, you are likely to create an error condition for the calling applications.

In general, the catalog update operates like a transaction. Before the update, the original attributes, including permissions, are in effect. After the update completes, the new attributes and permissions are in effect. In either case, any individual call to the stored procedure will run to completion under a consistent set of rules.

For example, if a call to stored procedure A is submitted at approximately the same time as a catalog update that removes the stored procedure, the call to stored procedure A will either complete successfully

or return an error indicating that the stored procedure no longer exists. If the stored procedure starts, it will not be interrupted by the catalog update.

In those cases where you need to make changes to a stored procedure that might negatively impact client applications, the following process is recommended:

1. Perform a catalog update that introduces a new stored procedure (with a new name) that implements the new function. Assuming the original stored procedure is A, let's call its replacement procedure B.
2. Update all client applications, replacing calls to procedure A with calls to procedure B, making the necessary code changes to accommodate any changed behavior or permissions.
3. Put the updated client applications into production.
4. Perform a second catalog update removing stored procedure A, now that all client application calls to the original procedure have been removed.

7.3. Updating the Database Using Save and Restore

If you need to make changes that are not supported by the **voltadmin update** command, it is still possible to modify the database schema using save and restore. You can modify the schema, including adding new constraints or modifying views, using the following steps:

1. Save the current data, using **voltadmin save**.
2. Shut down the database, using **voltadmin shutdown**.
3. Replace the application catalog.
4. Restart the database with the new catalog, using **voltadb create**.
5. Reload the data saved in Step #1 using **voltadmin restore**.

Using these steps, you can add or remove tables, columns and indexes. You can also change the datatype of existing columns, as long as you make sure the new type is compatible with the previous type (such as exchanging integer types or string types) and the new datatype has sufficient capacity for any values that currently exist within the database.

However, you cannot change the name of a column, add constraints to a column or change to a smaller datatype (such as changing from INTEGER to TINYINT) without the danger of losing data. To make these changes safely, it is better to add a new column with the desired settings and write a client application to move data from the original column to the new column, making sure to account for exceptions in data size or constraints.

See Section 9.1.3, “Changing the Database Schema or Cluster Configuration Using Save and Restore” for complete instructions for using save and restore to modify the database schema.

7.4. Updating the Hardware Configuration

Another change you are likely going to want to make at some point is changing the hardware configuration of your database cluster. Reasons for making these changes are:

- Increasing the number of nodes (and, as a consequence, capacity and throughput performance) of your database.

- Benchmarking the performance of your database application on different size clusters and with different numbers of partitions per node.

You can always change the number of nodes by saving the data (using a snapshot or command logging), editing the deployment file to specify the new number of nodes in the `hostcount` attribute of the `<cluster>` tag, then stopping and restarting the database using either the **recover** action or **voltadmin restore** command to reload the data. When doing benchmarking, where you need to change the number of partitions or other runtime options, this is the correct approach.

However, if you are simply adding nodes to the cluster to add capacity or increase performance, you can add the nodes while the database is running. Adding nodes "on the fly" is also known as *elastic* scaling.

To enable elastic scaling, you must first start the cluster with the option enabled by setting the `elastic` attribute of the `<cluster>` element to "enabled" in the deployment file. For example:

```
<deployment>
  <cluster    hostcount="3"
             sitesperhost="4"
             kfactor="0"
             elastic="enabled">

    [ . . . ]
```

After enabling elastic in the deployment file, you start the cluster as normal using the **voltadb create** or **recover** action.

When you are ready to extend the cluster by adding a node, you simply start the VoltDB database process on the new node using the **voltadb add** command specifying the name of one of the existing cluster nodes as the host. For example, if you are adding node `ServerX` to a cluster where `ServerA` is already a member, you can execute the following command on `ServerX`:

```
me@ServerX:~$ voltadb add host ServerA
```

Once the add action is initiated, the cluster performs the following tasks:

1. The cluster acknowledges the presence of a new server.
2. The active application catalog and deployment settings are sent to the new node.
3. Copies of all replicated tables and its share of the partitioned tables are sent to the new node.
4. Once all data is redistributed, the node enters the cluster as a fully participating member.

There are some important notes to consider when expanding the cluster using elastic scaling:

- Only clusters with a K-safety factor of zero — that is, no K-safety — can be expanded using elastic scaling. Highly available clusters must stop and restart to change the hardware configuration. This is a limitation of the initial release of elastic scaling and will be removed in subsequent releases.
- Elastic scaling does not currently support database replication (DR) or export.
- Adding nodes on the fly is a blocking operation. That means any transaction requests submitted after the operation begins must wait until all of the steps for adding the node are completed before the pending transactions are executed.
- Only one node can be added at a time.

Chapter 8. Security

Security is an important feature of any application. By default, VoltDB does not perform any security checks when a client application opens a connection to the database or invokes a stored procedure. This is convenient when developing and distributing an application on a private network.

However, on public or semi-private networks, it is important to make sure only known client applications are interacting with the database. VoltDB lets you control access to the database through settings in the schema and deployment files. The following sections explain how to enable and configure security for your VoltDB application.

8.1. How Security Works in VoltDB

When an application creates a connection to a VoltDB database (using `ClientFactory.clientCreate`), it passes a username and password as part of the client configuration. These parameters identify the client to the database and are used for authenticating access.

At runtime, if security is enabled, the username and password passed in by the client application are validated by the server against the users defined in the deployment file. If the client application passes in a valid username and password pair, the connection is established. When the application calls a stored procedure, permissions are checked again. If the schema identifies the user as being assigned a role having access to that stored procedure, the procedure is executed. If not, an error is returned to the calling application.

Note

VoltDB uses SHA-1 hashing rather than encryption when passing the username and password between the client and the server. The passwords are also hashed within the runtime catalog.

There are three steps to enabling security for a VoltDB application:

1. Add the `<security enabled="true"/>` tag to the deployment file to turn on authentication and authorization.
2. Define the users and roles you need to authenticate.
3. Define which roles have access to each stored procedure.

The following sections describe each step of this process, plus how to enable access to system procedures and ad hoc queries.

8.2. Enabling Authentication and Authorization

By default VoltDB does not perform authentication and client applications have full access to the database. To enable authentication, add the `<security>` tag to the deployment file:

```
<deployment>
  <security enabled="true"/>
  . . .
</deployment>
```

8.3. Defining Users and Roles

The key to security for VoltDB applications is the users and roles defined in the schema and deployment files. You define users in the deployment file and roles in the schema.

This split is deliberate because it allows you to define the overall security structure globally in the schema, assigning permissions to generic roles (such as admin, dbuser, apps, and so on). You then define specific users and assign them to the generic roles as part of the deployment. This way you can create one configuration (including cluster information and users) for development and testing, then move the application catalog to a different configuration and set of users for production by changing only one file: the deployment file.

You define users within the `<users> ... </users>` tag set in the deployment file. The syntax for defining users is as follows.

```
<deployment>
  <users>
    <user name="user-name"
          password="password-string"
          roles="role-name[,...]" />
    [ ... ]
  </users>
  ...
</deployment>
```

Include a `<user>` tag for every username/password pair you want to define.

Then within the schema you define the roles the users can belong to. You define roles with the CREATE ROLE statement.

```
CREATE ROLE role-name;
```

You specify which roles a user belongs to as part of the user definition in the deployment file using the roles attribute to the `<user>` tag. For example, the following code defines three users, assigning operator and developer to the admin role and developer and clientapp to the dbuser role. When a user is assigned to more than one role, you specify the role names as a comma-delimited list.

```
<deployment>
  <users>
    <user name="operator" password="mech" roles="admin" />
    <user name="developer" password="tech" roles="admin,dbuser" />
    <user name="clientapp" password="xyzy" roles="dbuser" />
  </users>
</deployment>
```

Two important notes concerning the assignment of users to roles:

- Users must be assigned at least one role, or else they have no permissions. (Permissions are assigned by role.)
- There must be a corresponding role defined in the schema for any roles listed in the deployment file.

8.4. Assigning Access to Stored Procedures

Once you define the users and roles you need, you assign them access to individual stored procedures using the ALLOW clause of the CREATE PROCEDURE statement in the schema. In the following example, users assigned to the roles admin and dbuser are permitted access to both the MyProc1 and MyProc2 procedures. Only users assigned the admin role have access to the MyProc3 procedure.

```
CREATE PROCEDURE ALLOW dbuser,admin FROM CLASS MyProc1;  
CREATE PROCEDURE ALLOW dbuser,admin FROM CLASS MyProc2;  
CREATE PROCEDURE ALLOW admin FROM CLASS MyProc3;
```

When security is enabled, you must specify access rights for each stored procedure. If a procedure declaration does not include an ALLOW clause, no access is allowed. In other words, calling applications will not be able to invoke that procedure.

8.5. Allowing Access to System Procedures, Ad Hoc Queries, and Default Procedures

There are several special procedures and functions available within VoltDB that are not called out in the schema. These features include system procedures, which all begin with an at sign (@) and perform special functions such as saving and restoring snapshots. (See Appendix F, *System Procedures* for more information about system procedures.) The other features that are not called out in the schema are the default INSERT, SELECT, UPDATE, and DELETE procedures created for each table and export.

By default, when security is not enabled, any calling application has access to these features. However, when you enable security, you must explicitly assign access to these functions as well.

Since there is no procedure definition in the schema, you assign access to these functions using the WITH clause when declaring the role. The four permissions enabled by the WITH clause are:

- SYSPROC — allows access to all system procedures
- ADHOC — allows access to the @AdHoc procedure only
- DEFAULTPROC — allows access to the default procedures for all tables
- EXPORT — allows access to the export connector for export clients

In the CREATE ROLE statement you enable access to these features by including the `adhoc`, `defaultproc`, `export`, and `sysproc` keywords in the WITH clause. (The default, if security is enabled and the keyword is not specified, is that the role is not allowed access to the corresponding feature.)

Note that the permissions are additive. So if a user is assigned one role that allows access to `adhoc` but not `sysproc`, but that user also is assigned another role that allows `sysproc`, the user has both permissions.

The following example assigns access to all system procedures to members of the `admin` role, access to the `adhoc` procedure and default procedures to members of the `dbuser` role, and no access to system procedures but access to default procedures for all other users.

```
CREATE ROLE admin WITH sysproc;  
CREATE ROLE dbuser WITH adhoc, defaultproc;  
CREATE ROLE apps WITH defaultproc;
```

Chapter 9. Saving & Restoring a VoltDB Database

There are times when it is necessary to save the contents of a VoltDB database to disk and then restore it. For example, if the cluster needs to be shut down for maintenance, you may want to save the current state of the database before shutting down the cluster and then restore the database once the cluster comes back online. Performing periodic backups of the data can also provide a fallback in case of unexpected failures — either physical failures, such as power outages, or logic errors where a client application mistakenly corrupts the database contents.

VoltDB provides shell commands, system procedures, and an automated snapshot feature that help you perform these operations. The following sections explain how to save and restore a running VoltDB cluster, either manually or automatically.

9.1. Performing a Manual Save and Restore of a VoltDB Cluster

Manually saving and restoring a VoltDB database is useful when you need to do maintenance on the database itself or the cluster it runs on. The normal use of save and restore, when performing such a maintenance operation, is as follows:

1. Stop database activities (using `pause`).
2. Use `save` to write a snapshot of the current data to disk.
3. Shutdown the cluster.
4. Make changes to the VoltDB catalog and/or deployment file (if desired).
5. Restart the cluster in admin mode.
6. Restore the previous snapshot.
7. Restart client activity (using `resume`).

The key is to make sure that all database activity is stopped before the save and shutdown are performed. This ensures that no further changes to the database are made (and therefore lost) after the save and before the shutdown. Similarly, it is important that no client activity starts until the database has started and the restore operation completes.

Save and restore operations are performed either by calling VoltDB system procedures or using the corresponding **voltadmin** shell commands. In most cases, the shell commands are simpler since they do not require program code to use. Therefore, this chapter uses **voltadmin** commands in the examples. If you are interested in programming the save and restore procedures, see Appendix F, *System Procedures* for more information about the corresponding system procedures.

When you issue a `save` command, you specify a path where the data will be saved and a unique identifier for tagging the files. VoltDB then saves the current data on each node of the cluster to a set of files at the specified location (using the unique identifier as a prefix to the file names). This set of files is referred to as a snapshot, since it contains a complete record of the database for a given point in time (when the save operation was performed).

The `--blocking` option lets you specify whether the save operation should block other transactions until it completes. In the case of manual saves, it is a good idea to use this option since you do not want additional changes made to the database during the save operation.

Note that every node in the cluster uses the same absolute path, so the path specified must be valid, must exist on every node, and must not already contain data from any previous saves using the same unique identifier, or the save will fail.

When you issue a restore command, you specify the same absolute path and unique identifier used when creating the snapshot. VoltDB checks to make sure the appropriate save set exists on each node, then restores the data into memory.

9.1.1. How to Save the Contents of a VoltDB Database

To save the contents of a VoltDB database, use the **voltadmin save** command. The following example creates a snapshot at the path `/tmp/voltdb/backup` using the unique identifier *TestSnapshot*.

```
$ voltadmin save --blocking /tmp/voltdb/backup "TestSnapshot"
```

In this example, the command tells the save operation to block all other transactions until it completes. It is possible to save the contents without blocking other transactions (which is what automated snapshots do). However, when performing a manual save prior to shutting down, it is normal to block other transactions to ensure you save a known state of the database.

Note that it is possible for the save operation to succeed on some nodes of the cluster and not others. When you issue the **voltadmin save** command, VoltDB displays messages from each partition indicating the status of the save operation. If there are any issues that would stop the process from starting, such as a bad file path, they are displayed on the console. It is a good practice to examine these messages to make sure all partitions are saved as expected.

9.1.2. How to Restore the Contents of a VoltDB Database

To restore a VoltDB database from a snapshot previously created by a save operation, you use the **voltadmin restore** command. You must specify the same pathname and unique identifier used during the save.

The following example restores the snapshot created by the example in Section 9.1.1.

```
$ voltadmin restore /tmp/voltdb/backup "TestSnapshot"
```

As with save operations, it is always a good idea to check the status information displayed by the command to ensure the operation completed as expected.

9.1.3. Changing the Database Schema or Cluster Configuration Using Save and Restore

Between a save and a restore, it is possible to make selected changes to the database. You can:

- Add nodes to the cluster
- Modify the database schema
- Add, remove, or modify stored procedures

To make these changes, you must, as appropriate, edit the database schema, the procedure source files, or the deployment file. You can then recompile the application catalog and distribute the updated catalog and deployment file to the cluster nodes before restarting the cluster and performing the restore.

9.1.3.1. Adding Nodes to the Database

To add nodes to the cluster, use the following procedure:

- Save the database.
- Edit the deployment file, specifying the new number of nodes in the `hostcount` attribute of the `<cluster>` tag.
- Restart the cluster (including the new nodes).
- Issue a restore command.

When the snapshot is restored, the database (and partitions) are redistributed over the new cluster configuration.

It is also possible to remove nodes from the cluster using this procedure. However, to make sure that no data is lost in the process, you must copy the snapshot files from the nodes that are being removed to one of the nodes that is remaining in the cluster. This way, the restore operation can find and restore the data from partitions on the missing nodes.

9.1.3.2. Modifying the Database Schema and Stored Procedures

To modify the database schema or stored procedures, make the appropriate changes to the source files (that is, the database DDL and the stored procedure Java source files), then recompile the application catalog. However, you can only make certain modifications to the database schema. Specifically, you can:

- Add or remove tables.
- Add or remove columns from tables.
- Change the datatypes of columns, assuming the two datatypes are compatible. (That is, the data can be converted from the old to the new type. For example, extending the length of `VARCHAR` columns or converting between two numeric datatypes.)

Note that you *cannot* rename tables or columns and retain the data. If you rename a table or column, it is equivalent to deleting the original table/column (and its data) and adding a new one. Two other important points to note when modifying the database structure are:

- When existing rows are restored to tables where new columns have been added, the new columns are filled with either the default value (if defined by the schema) or nulls.
- When changing the datatypes of columns, it is possible to decrease the datatype size (for example, going from an `INT` to an `TINYINT`). However, if any existing values exceed the capacity of the new datatype (such as an integer value of 5,000 where the datatype has been changed to `TINYINT`), the entire restore will fail.

If you remove or modify stored procedures (particularly if you change the number and/or datatype of the parameters), you must make sure the corresponding changes are made to all client applications as well.

9.2. Scheduling Automated Snapshots

Save and restore are useful when planning for scheduled down times. However, these functions are also important for reducing the risk from unexpected outages. VoltDB assists in contingency planning and recovery from such worst case scenarios as power failures, fatal system errors, or data corruption due to application logic errors.

In these cases, the database stops unexpectedly or becomes unreliable. By automatically generating snapshots at set intervals, VoltDB gives you the ability to restore the database to a previous valid state.

You schedule automated snapshots of the database as part of the deployment file. The `<snapshot>` tag lets you specify:

- The frequency of the snapshots. You can specify any whole number of seconds, minutes, or hours (using the suffix "s", "m", or "h", respectively, to denote the unit of measure). For example "3600s", "60m", and "1h" are all equivalent.
- The unique identifier to use as a prefix for the snapshot files.
- The number of snapshots to retain. Snapshots are marked with a timestamp (as part of the file names), so multiple snapshots can be saved. The `retain` attribute lets you specify how many snapshots to keep. Older snapshots are purged once this limit is reached.

The following example enables automated snapshots every thirty minutes using the prefix "flightsave" and keeping only the three most recent snapshots.

```
<snapshot prefix="flightsave"
          frequency="30m"
          retain="3"
/>
```

By default, automated snapshots are stored in a subfolder of the VoltDB default path (as described in Section 6.1.2, "Configuring Paths for Runtime Features"). You can save the snapshots to a specific path by adding the `<snapshots>` tag within to the `<paths>...</paths>` tag set. For example, the following example defines the path for automated snapshots as `/etc/voltdb/autobackup/`.

```
<paths>
  <snapshots path="/etc/voltdb/autobackup/" />
</paths>
```

9.3. Managing Snapshots

VoltDB does not delete snapshots after they are restored; the snapshot files remain on each node of the cluster. For automated snapshots, the oldest snapshot files are purged according to the settings in the deployment file. But if you create snapshots manually or if you change the directory path or the prefix for automated snapshots, the old snapshots will also be left on the cluster.

To simplify maintenance, it is a good idea to observe certain guidelines when using save and restore:

- Create dedicated directories for use as the paths for VoltDB snapshots.
- Use separate directories for manual and automated snapshots (to avoid conflicts in file names).
- Do not store any other files in the directories used for VoltDB snapshots.
- Periodically cleanup the directories by deleting obsolete, unused snapshots.

You can delete snapshots manually. To delete a snapshot, use the unique identifier, which is applied as a filename prefix, to find all of the files in the snapshot. For example, the following commands remove the snapshot with the ID `TestSave` from the directory `/etc/voltdb/backup/`. Note that VoltDB separates the prefix from the remainder of the file name with a dash for manual snapshots:

```
$ rm /etc/voltdb/backup/TestSave-*
```

However, it is easier if you use the system procedures VoltDB provides for managing snapshots. If you delete snapshots manually, you must make sure you execute the commands on all nodes of the cluster. When you use the system procedures, VoltDB distributes the operations across the cluster automatically.

VoltDB provides several system procedures to assist with the management of snapshots:

- `@SnapshotStatus` provides information about the most recently performed snapshots for the current database. The response from `SnapshotStatus` includes information about up to ten recent snapshots, including their location, when they were created, how long the save took, whether they completed successfully, and the size of the individual files that make up the snapshot. See the reference section on `@SnapshotStatus` for details.
- `@SnapshotScan` lists all of the snapshots available in a specified directory path. You can use this system procedure to determine what snapshots exist and, as a consequence, which ought to be deleted. See the reference section on `@SnapshotScan` for details.
- `@SnapshotDelete` deletes one or more snapshots based on the paths and prefixes you provide. The parameters to the system procedure are two string arrays. The first array specifies one or more directory paths. The second array specifies one or more prefixes. The array elements are taken in pairs to determine which snapshots to delete. For example, if the first array contains paths A, B, and C and the second array contains the unique identifiers X, Y, and Z, the following three snapshots will be deleted: A/X, B/Y, and C/Z. See the reference section on `@SnapshotDelete` for details.

9.4. Special Notes Concerning Save and Restore

The following are special considerations concerning save and restore that are important to keep in mind:

- Save and restore do not check the cluster health (whether all nodes exist and are running) before executing. The user can find out what nodes were saved by looking at the messages displayed by the save operation.
- Both the save and restore calls do a pre-check to see if the action is likely to succeed before the actual save/restore is attempted. For save, VoltDB checks to see if the path exists, if there is any data that might be overwritten, and if it has write access to the directory. For restore, VoltDB verifies that the saved data can be restored completely.
- You should use separate directories for manual and automated snapshots to avoid naming conflicts.
- It is possible to provide additional protection against failure by copying the automated snapshots to remote locations. Automated snapshots are saved locally on the cluster. However, you can set up a network process to periodically copy the snapshot files to a remote system. (Be sure to copy the files from all of the cluster nodes.) Another approach would be to save the snapshots to a SAN disk that is already set up to replicate to another location. (For example, using iSCSI.)

Chapter 10. Command Logging and Recovery

By executing transactions in memory, VoltDB, frees itself from much of the management overhead and I/O costs of traditional database products. However, accidents do happen and it is important that the contents of the database be safeguarded against loss or corruption.

Snapshots provide one mechanism for safeguarding your data, by creating a point-in-time copy of the database contents. But what happens to the transactions that occur between snapshots?

Command logging provides a more complete solution to the durability and availability of your VoltDB database. Command logging keeps a record of every transaction (that is, stored procedure) as it is executed. Then, if the servers fail for any reason, the database can restore the last snapshot and "replay" the subsequent logs to re-establish the database contents in their entirety.

The key to command logging is that it logs the invocations, not the consequences, of the transactions. A single stored procedure can include many individual SQL statements and each SQL statement can modify hundreds or thousands of table rows. By recording only the invocation, the command logs are kept to a bare minimum, limiting the impact the disk I/O will have on performance.


However, any additional processing can impact overall performance, especially when it involves disk I/O. So it is important to understand the tradeoffs concerning different aspects of command logging and how it interacts with the hardware and any other options you are utilizing. The following sections explain how command logging works and how to configure it to meet your specific needs.

10.1. How Command Logging Works

When you enable command logging, VoltDB keeps a log of every transaction (that is, stored procedure) invocation. At first, the log of the invocations are held in memory. Then, at a set interval the logs are physically written to disk. Of course, at a high transaction rate, even limiting the logs to just invocations, the logs begin to fill up. So at a broader interval, the server initiates a snapshot. Once the snapshot is complete, the command logging process is able to free up — or "truncate" — the log keeping only a record of procedure invocations since the last snapshot.

This process can continue indefinitely, using snapshots as a baseline and loading and truncating the command logs for all transactions since the last snapshot.

Figure 10.1. Command Logging in Action




The frequency with which the transactions are written to the command log is configurable (as described in Section 10.3, "Configuring Command Logging for Optimal Performance"). By adjusting the frequency and

type of logging (synchronous or asynchronous) you can balance the performance needs of your application against the level of durability desired.

In reverse, when it is time to "replay" the logs, if you start the database with the **recover** action (as described in Section 6.5.2, "Command Logging and Recovery") once the server nodes establish a quorum, they start by restoring the most recent snapshot. Once the snapshot is restored, they then replay all of the transactions in the log since that snapshot.

Figure 10.2. Recovery in Action



10.2. Enabling Command Logging

Command logging is not enabled by default. To enable command logging, you add the `<commandlog>` element to the deployment file. For example:

```
<deployment>
  <cluster hostcount="4" sitesperhost="2" kfactor="1" />
  <commandlog enabled="true"/>
</deployment>
```

In its simplest form, the `<commandlog/>` tag enables command logging using the default configuration. You can use the `enabled` attribute to explicitly enable or disable the feature (as in the previous example), or you can add attributes and child elements to control specific characteristics of command logging. The following section describes those options in detail.

10.3. Configuring Command Logging for Optimal Performance

Command logging can provide complete durability, preserving a record of every transaction that is completed before the database stops. However, the amount of durability must be balanced against the performance impact and hardware requirements to achieve effective I/O.

VoltDB provides three settings you can use to optimize command logging:

- The amount of disk space allocated to the command logs
- The frequency between writes to the command logs
- Whether logging is synchronous or asynchronous

The following sections describe these options. A fourth section discusses the impact of storage hardware on the different logging options.

10.3.1. Log Size

The command log size specifies how much disk space is preallocated for storing the logs on disk. The logs are divided into three "segments" Once a segment is full, it is written to a snapshot (as shown in Figure 10.1, "Command Logging in Action").

For most workloads, the default log size of one gigabyte is sufficient. However, if your workload writes large volumes of data or uses large strings for queries (so the procedure invocations include large parameter values), the log segments fill up very quickly. When this happens, VoltDB can end up snapshotting continuously, because by the time one snapshot finishes, the next log segment is full.

To avoid this situation, you can increase the total log size, to reduce the frequency of snapshots. You define the log size in the deployment file using the `logsize` attribute of the `<commandlog>` tag. Specify the desired log size as an integer number of megabytes. For example:

```
<commandlog enabled="true" logsize="3072" />
```

When increasing the log size, be aware that the larger the log, the longer it may take to recover the database since any transactions in the log since the last snapshot must be replayed before the recovery is complete. So, while reducing the frequency of snapshots, you also may be increasing the time needed to restart.

The minimum log size is three megabytes. Note that the log size specifies the *initial* size. If the existing segments are filled before a snapshot can truncate the logs, the server will allocate additional segments.

10.3.2. Log Frequency

The log frequency specifies how often transactions are written to the command log. In other words, the interval between writes, as shown in Figure 10.1, "Command Logging in Action". You can specify the frequency in either or both time and number of transactions.

For example, you might specify that the command log is written every 200 milliseconds or every 500 transactions, whichever comes first. You do this by adding the `<frequency>` element as a child of `<commandlog>` and specifying the individual frequencies as attributes. For example:

```
<commandlog enabled="true">  
  <frequency time="200" transactions="500"/>  
</commandlog>
```

Time frequency is specified in milliseconds and transaction frequency is specified as the number of transactions. You can specify either or both types of frequency. If you specify both, whichever limit is reached first initiates a write.

10.3.3. Synchronous vs. Asynchronous Logging

If the command logs are being written *asynchronously* (which is the default), results are returned to the client applications as soon as the transactions are completed. This allows the transactions to execute uninterrupted.

However, with asynchronous logging there is always the possibility that a catastrophic event (such as a power failure) could cause the cluster to fail. In that case, any transactions completed since the last write and before the failure would be lost. The smaller the frequency, the less data that could be lost. This is how you "dial up" the amount of durability you want using the configuration options for command logging.

In some cases, no loss of data is acceptable. For those situations, it is best to use *synchronous logging*. When you select synchronous logging, no results are returned to the client applications until those transactions

are written to the log. In other words, the results for all of the transactions since the last write are held on the server until the next write occurs.

The advantage of synchronous logging is that no transaction is "complete" and reported back to the calling application until it is guaranteed to be logged — no transactions are lost. The obvious disadvantage of synchronous logging is that the interval between writes (i.e. the frequency) while the results are held, adds to the latency of the transactions. To reduce the penalty of synchronous logging, you need to reduce the frequency.

When using synchronous logging, it is recommended that the frequency be limited to between 1 and 4 milliseconds to avoid adding undue latency to the transaction rate. A frequency of 1 or 2 milliseconds should have little or no measurable affect on overall latency. However, low frequencies can only be achieved effectively when using appropriate hardware (as discussed in the next section, Section 10.3.4, "Hardware Considerations").

To select synchronous logging, use the `synchronous` attribute of the `<commandlog>` tag. For example:

```
<commandlog enabled="true" synchronous="true" >
  <frequency time="2"/>
</commandlog>
```

10.3.4. Hardware Considerations

Clearly, synchronous logging is preferable since it provides complete durability. However, to avoid negatively impacting database performance you must not only use very low frequencies, but you must have storage hardware that is capable of handling frequent, small writes. Attempting to use aggressively low log frequencies with storage devices that cannot keep up will also hurt transaction throughput and latency.

Standard, uncached storage devices can quickly become overwhelmed with frequent writes. So you should not use low frequencies (and therefore synchronous logging) with slower storage devices. Similarly, if the command logs are competing for the device with other disk I/O, performance will suffer. So do not write the command logs to the same device that is being used for other I/O, such as snapshots or export overflow.

On the other hand, fast, cached devices such as disks with a battery-backed cache, are capable of handling frequent writes. So it is strongly recommended that you use such devices when using synchronous logging.

To specify where the command logs and their associated snapshots are written, you use tags within the `<paths>...</paths>` tag set. For example, the following example specifies that the logs are written to `/fastdisk/voltdblog` and the snapshots are written to `/opt/voltdb/cmdsnaps`:

```
<paths>
  <commandlog path="/fastdisk/voltdblog/" />
  <commandlogsnapshot path="/opt/voltdb/cmdsnaps/" />
</paths>
```

Note that the default paths for the command logs and the command log snapshots are both subfolders of the `voltdbroot` directory. To avoid overloading a single device on production servers, it is recommended that you specify an explicit path for the command logs, at a minimum, and preferably for both logs and snapshots.

To summarize, the rules for balancing command logging with performance and throughput on production databases are:

- Use asynchronous logging with slower storage devices.

- Write command logs to a dedicated device. Do not write logs and snapshots to the same device.
- Use low (1-2 millisecond) frequencies when performing synchronous logging.
- Use moderate (100 millisecond or greater) frequencies when performing asynchronous logging.

Chapter 11. Availability

Durability is one of the four key ACID attributes required to ensure the accurate and reliable operation of a transactional database. Durability refers to the ability to maintain database consistency and availability in the face of external problems, such as hardware or operating system failure. Durability is provided by four features of VoltDB: snapshots, command logging, K-safety, and disaster recovery through database replication.

- *Snapshots* are a "snapshot" of the data within the database at a given point in time written to disk. You can use these snapshot files to restore the database to a previous, known state after a failure which brings down the database. The snapshots are guaranteed to be transactionally consistent at the point at which the snapshot was taken. Chapter 9, *Saving & Restoring a VoltDB Database* describes how to create and restore database snapshots.
- *Command Logging* is a feature where, in addition to periodic snapshots, the system keeps a log of every stored procedure (or "command") as it is invoked. If, for any reason, the servers fail, they can "replay" the log on startup to reinstate the database contents completely rather than just to an arbitrary point-in-time. Chapter 10, *Command Logging and Recovery* describes how to enable, configure, and replay command logs.
- *K-safety* refers to the practice of duplicating database partitions so that the database can withstand the loss of cluster nodes without interrupting the service. For example, a K value of zero means that there is no duplication and losing any servers will result in a loss of data and database operations. If there are two copies of every partition (a K value of one), then the cluster can withstand the loss of at least one node (and possibly more) without any interruption in service.
- *Database Replication* is similar to K-safety, since it involves replicating data. However, rather than creating redundant partitions within a single database, database replication involves creating and maintaining a complete copy of the entire database. Database replication has a number of uses, but specifically in terms of durability, replication lets you maintain two copies of the database in separate geographic locations. In case of catastrophic events, such as fires, earthquakes, or large scale power outages, the replica can be used as a replacement for a disabled cluster.

Previous chapters described snapshots and command logging. The next chapter describes how you can use database replication for disaster recovery. This chapter explains how K-safety works, how to configure your VoltDB database for different values of K, and how to recover in the case of a system failure.

11.1. How K-Safety Works

K-safety involves duplicating database partitions so that if a partition is lost (either due to hardware or software problems) the database can continue to function with the remaining duplicates. In the case of VoltDB, the duplicate partitions are fully functioning members of the cluster, including all read and write operations that apply to those partitions. (In other words, the duplicates function as peers rather than in a master-slave relationship.)

It is also important to note that K-safety is different than WAN replication. In replication the entire database cluster is replicated (usually at a remote location to provide for disaster recovery in case the entire cluster or site goes down due to catastrophic failure of some type).

In replication, the replicated cluster operates independently and cannot assist when only part of the active cluster fails. The replicate is intended to take over only when the primary database cluster fails entirely. So, in cases where the database is mission critical, it is not uncommon to use both K-safety and replication to achieve the highest levels of service.

To achieve $K=1$, it is necessary to duplicate all partitions. (If you don't, failure of a node that contains a non-duplicated partition would cause the database to fail.) Similarly, $K=2$ requires two duplicates of every partition, and so on.

What happens during normal operations is that any work assigned to a duplicated partition is sent to all copies (as shown in Figure 11.1, “K-Safety in Action”). If a node fails, the database continues to function sending the work to the unaffected copies of the partition.

Figure 11.1. K-Safety in Action



11.2. Enabling K-Safety

You specify the desired K-safety value as part of the cluster configuration in the VoltDB deployment file for your application. By default, VoltDB uses a K-safety value of zero (no duplicate partitions). You can specify a larger K-safety value using the `kfactor` attribute of the `<cluster>` tag. For example, in the following deployment file, the K-safety value for a 6-node cluster with 4 partitions per node is set to 2:

```
<?xml version="1.0"?>
<deployment>
  <cluster hostcount="6"
           sitesperhost="4"
           kfactor="2"
  />
</deployment>
```

When you start the database specifying a K-safety value greater than zero, the appropriate number of partitions out of the cluster will be assigned as duplicates. For example, in the preceding case where there are 6 nodes and 4 partitions per node, there are a total of 24 partitions. With $K=1$, half of those partitions (12) will be assigned as duplicates of the other half. If K is increased to 2, the cluster would be divided into 3 copies consisting of 8 partitions each.

The important point to note when setting the K value is that, if you do not change the hardware configuration, you are dividing the available partitions among the duplicate copies. Therefore performance (and capacity) will be proportionally decreased as K-safety is increased. So running K=1 on a 6-node cluster will be approximately equivalent to running a 3-node cluster with K=0.

If you wish to increase reliability without impacting performance, you must increase the cluster size to provide the appropriate capacity to accommodate for K-safety.

11.2.1. What Happens When You Enable K-Safety

Of course, to ensure a system failure does not impact the database, not only do the partitions need to be duplicated, but VoltDB must ensure that the duplicates are kept on separate nodes of the cluster. To achieve this, VoltDB calculates the maximum number of unique partitions that can be created, given the number of nodes, partitions per node, and the desired K-safety value.

When the number of nodes is an integral multiple of the duplicates needed, this is easy to calculate. For example, if you have a six node cluster and choose K=1, VoltDB will create two instances of three nodes each. If you choose K=2, VoltDB will create three instances of two nodes each. And so on.

If the number of nodes is not a multiple of the number of duplicates, VoltDB does its best to distribute the partitions evenly. For example, if you have a three node cluster with two partitions per node, when you ask for K=1 (in other words, two of every partition), VoltDB will duplicate three partitions, distributing the six total partitions across the three nodes.

11.2.2. Calculating the Appropriate Number of Nodes for K-Safety

By now it should be clear that there is a correlation between the K value and the number of nodes and partitions in the cluster. Ideally, the number of nodes is a multiple of the number of copies needed (in other words, the K value plus one). This is both the easiest configuration to understand and manage.

However, if the number of nodes is not an exact multiple, VoltDB distributes the duplicated partitions across the cluster using the largest number of unique partitions possible. This is the highest whole integer where the number of unique partitions is equal to the total number of partitions divided by the needed number of copies:

$$\text{Unique partitions} = (\text{nodes} * \text{partitions/node}) / (K + 1)$$

Therefore, when you specify a cluster size that is not a multiple of K+1, but where the total number of partitions is, VoltDB will use all of the partitions to achieve the required K-safety value.

Note that the total number of partitions must be a whole multiple of the number of copies (that is, K+1). If neither the number of nodes nor the total number of partitions is divisible by K+1, then VoltDB will not let the cluster start and will display an appropriate error message. For example, if the deployment file specifies a three node cluster with 3 sites per host and a K-safety value of 1, the cluster cannot start because the total number of partitions (3X3=9) is not a multiple of the number of copies (K+1=2). To start the cluster, you must either increase the K-safety value to 2 (so the number of copies is 3) or change the sites per host to 2 or 4 so the total number of partitions is divisible by 2.

Finally, if you specify a K value higher than the available number of nodes, it is not possible to achieve the requested K-safety. Even if there are enough partitions to create the requested duplicates, VoltDB cannot distribute the duplicates to distinct nodes. For example, if you have a 3 node cluster with 4 partitions per node (12 total partitions), there are enough partitions to achieve a K value of 3, but not without some

duplicates residing on the same node. In this situation, VoltDB issues an error message. You must either reduce the K-safety or increase the number of nodes.

11.3. Recovering from System Failures

When running without K-safety (in other words, a K-safety value of zero) any node failure is fatal and will bring down the database (since there are no longer enough partitions to maintain operation). When running with K-safety on, if a node goes down, the remaining nodes of the database cluster log an error indicating that a node has failed.

By default, these error messages are logged to the console terminal. Since the loss of one or more nodes reduces the reliability of the cluster, you may want to increase the urgency of these messages. For example, you can configure a separate Log4J appender (such as the SMTP appender) to report node failure messages. To do this, you should configure the appender to handle messages of class `HOST` and severity level `ERROR` or greater. See Chapter 14, *Logging and Analyzing Activity in a VoltDB Database* for more information about configuring logging.

When a node fails with K-safety enabled, the database continues to operate. But at the earliest possible convenience, you should repair (or replace) the failed node.

To replace a failed node to a running VoltDB cluster, you restart the VoltDB server process specifying the deployment file, **rejoin** as the start action, and the address of one of the remaining nodes of the cluster as the *host*. For example, to rejoin a node to the VoltDB cluster where `myclusternode5` is one of the current member nodes, you use the following command:

```
$ voltdb rejoin host myclusternode5 \  
      deployment mydeployment.xml
```

Note that the node you specify may be any active cluster node; it *does not* have to be the node identified as the host when the cluster was originally started. Also, the deployment file you specify must be the currently active deployment settings for the running database cluster.

11.3.1. What Happens When a Node Rejoins the Cluster

When you issue the rejoin command, the node first rejoins the cluster, then retrieves a copy of the application catalog and the appropriate data for its partitions from other nodes in the cluster. Rejoining the cluster only takes seconds and once this is done and the catalog is received, the node can accept and distribute stored procedure requests like any other member.

However, the new node will not actively participate in the work until a full working copy of its partition data is received. What's more, the update process for each partition operates as a single transaction and will block further transactions on the partition which is providing the data.

While the node is rejoining and being updated, the cluster continues to accept work. If the work queue gets filled (because the update is blocking further work), the client applications will experience back pressure. Under normal conditions, this means the calls to submit stored procedures with the `callProcedure` method (either synchronously or asynchronously) will wait until the back pressure clears before returning control to the calling application.

The time this update process takes varies in length depending on the volume of data involved and network bandwidth. However, the process should not take more than a few minutes.

More importantly, the cluster is not fully K-safe until the restoration is complete. For example, if the cluster was established with a K-safety value of two and one node failed, until that node rejoins and is updated,

the cluster is operating with a K-safety value of one. Once the node is up to date, the cluster becomes fully operational and the original K-safety is restored.

11.3.2. Rejoining a "Live" Cluster

An alternative to the work interruption of a blocking rejoin is to perform a *live rejoin*. Live rejoin separates the rejoin process from the standard transactional workflow, allowing the database to continue operating with a minimal impact to throughput or latency. The advantage of a live rejoin is that the database remains available and responsive to client applications throughout the rejoin procedure. The deficit of a live rejoin is that, for large datasets, the rejoin process can take longer to complete than with a blocking rejoin.

To perform a live rejoin, you add the `live` keyword to the command line. For example, the following command performs a live rejoin to the database cluster including the node `myclusternode5`:

```
$ voltdb live rejoin host myclusternode5 \  
      deployment mydeployment.xml
```

In rare cases, if the database is near capacity in terms of throughput, a live rejoin cannot keep up with the ongoing changes made to the data. If this happens, VoltDB reports that the live rejoin cannot complete and you must wait until database activity subsides or you can safely perform a regular, blocking, rejoin to reconnect the server.

11.3.3. Where and When Recovery May Fail

It is possible to rejoin any appropriately configured node to the cluster. It does not have to be the same physical machine that failed. This way, if a node fails for hardware reasons, it is possible to replace it in the cluster immediately with a new node, giving you time to diagnose and repair the faulty hardware without endangering the database itself.

It is also possible, when doing blocking rejoins, to rejoin multiple nodes simultaneously, if multiple nodes fail. That is, assuming the cluster is still viable after the failures. As long as there is at least one active copy of every partition, the cluster will continue to operate and be available for nodes to rejoin. Note that with live rejoin, only one node can rejoin at a time.

There are a few conditions in which the rejoin operation may fail. Those situations include the following:

- Insufficient K-safety

If the database is running without K-safety, or more nodes fail simultaneously than the cluster is capable of sustaining, the entire cluster will fail and must be restarted from scratch. (At a minimum, a VoltDB database running with K-safety can withstand at least as many simultaneous failures as the K-safety value. It may be able to withstand more node failures, depending upon the specific situation. But the K-safety value tells you the minimum number of node failures that the cluster can withstand.)

- Mismatched deployment file

If the deployment file that you specify when issuing the rejoin command does not match the current deployment configuration of the database, the cluster will refuse to let the node rejoin.

- More nodes attempt to rejoin than have failed

If one or more nodes fail, the cluster will accept rejoin requests from as many nodes as failed. For example, if one node fails, the first node requesting to rejoin with the appropriate catalog and deployment file will be accepted. Once the cluster is back to the correct number of nodes, any further requests to rejoin will be rejected. (This is the same behavior as if you tried to add more nodes than specified in the deployment file when initially starting the database.)

- The rejoining node does not specify a valid username and/or password

When rejoining a cluster with security enabled, you must specify a valid username and password when issuing the rejoin command. The username and password you specify must have sufficient privileges to execute system procedures. If not, the rejoin request will be rejected and an appropriate error message displayed.

11.4. Avoiding Network Partitions

VoltDB achieves scalability by creating a tightly bound network of servers that distribute both data and processing. When you configure and manage your own server hardware, you can ensure that the cluster resides on a single network switch, guaranteeing the best network connection between nodes and reducing the possibility of network faults interfering with communication.

However, there are situations where this is not the case. For example, if you run VoltDB "in the cloud", you may not control or even know what is the physical configuration of your cluster.

The danger is that a network fault — between switches, for example — can interrupt communication between nodes in the cluster. The server nodes continue to run, and may even be able to communicate with others nodes on their side of the fault, but cannot "see" the rest of the cluster. In fact, both halves of the cluster think that the other half has failed. This condition is known as a *network partition*.


11.4.1. K-Safety and Network Partitions

When you run a VoltDB cluster without availability (in other words, no K-safety) the danger of a network partition is simple: loss of the database. Any node failure makes the cluster incomplete and the database will stop. You will need to reestablish network communications, restart VoltDB, and restore the database from the last snapshot.

However, if you are running a cluster with K-safety, it is possible that when a network partition occurs, the two separate segments of the cluster might have enough partitions each to continue running, each thinking the other group of nodes has failed.

For example, if you have a 3 node cluster with 2 sites per node, and a K-safety value of 2, each node is a separate, self-sustaining copy of the database, as shown in Figure 11.2, "Network Partition". If a network partition separates nodes A and B from node C, each segment has sufficient partitions remaining to sustain the database. Nodes A and B think node C has failed; node C thinks that nodes A and B have failed.

Figure 11.2. Network Partition



The problem is that you never want two separate copies of the database continuing to operate and accepting requests thinking they are the only viable copy. If the cluster is physically on a single network switch, the threat of a network partition is reduced. But if the cluster is on multiple switches, the risk increases significantly and must be accounted for.

11.4.2. Using Network Fault Protection

VoltDB provides a mechanism for guaranteeing that a network partition does not accidentally create two separate copies of the database. The feature is called network fault protection.

Because the consequences of a partition are so severe, use of network partition detection is strongly recommended and VoltDB enables partition detection by default. In addition it is recommended that, where possible, K-safe cluster by configured with an odd number of nodes.

However, it is possible to disable network fault protection in the deployment file, if you choose. You enable and disable partition detection using the `<partition-detection>` tag. The `<partition-detection>` tag is a child of `<deployment>` and peer of `<cluster>`. For example:

```
<deployment>
  <cluster hostcount="4"
    sitesperhost="2"
    kfactor="1" />
  <partition-detection enabled="true">
    <snapshot prefix="netfault"/>
  </partition-detection>
</deployment>
```

If a partition is detected, the affected nodes automatically do a snapshot of the current database before shutting down. You can use the `<snapshot>` tag to specify the file prefix for the snapshot files. If you do not explicitly enable partition detection, the default prefix is "partition_detection".

Network partition snapshots are saved to the same directory as automated snapshots. By default, this is a subfolder of the VoltDB root directory as described in Section 6.1.2, "Configuring Paths for Runtime Features". However, you can select a specific path using the `<paths>` tag set. For example, the following example sets the path for snapshots to `/opt/voltdb/snapshots/`.


```
<partition-detection enabled="true">
  <snapshot prefix="netfaultsave"/>
</partition-detection>
<paths>
  <snapshots path="/opt/voltdb/snapshots/" />
</paths>
```

When network fault protection is enabled, and a fault is detected (either due to a network fault or one or more servers failing), any viable segment of the cluster will perform the following steps:

1. Determine what nodes are missing
2. Determine if the missing nodes are also a viable self-sustained cluster. If so...
3. Determine which segment is the larger segment (that is, contains more nodes).
 - If the current segment is larger, continue to operate assuming the nodes in the smaller segment have failed.
 - If the other segment is larger, perform a snapshot of the current database content and shutdown to avoid creating two separate copies of the database.

For example, in the case shown in Figure 11.2, “Network Partition”, if a network partition separates nodes A and B from C, the larger segment (nodes A and B) will continue to run and node C will write a snapshot and shutdown (as shown in Figure 11.3, “Network Fault Protection in Action”).

Figure 11.3. Network Fault Protection in Action



If a network partition creates two viable segments of the same size (for example, if a four node cluster is split into two two-node segments), a special case is invoked where one segment is uniquely chosen to continue, based on the internal numbering of the host nodes. Thereby ensuring that only one viable segment of the partitioned database continues.

Network fault protection is a very valuable tool when running VoltDB clusters in a distributed or uncontrolled environment where network partitions may occur. The one downside is that there is no way to differentiate between network partitions and actual node failures. In the case where network fault protection is turned on and no network partition occurs but a large number of nodes actually fail, the remaining nodes may believe they are the smaller segment. In this case, the remaining nodes will shut themselves down to avoid partitioning.

For example, in the previous case shown in Figure 11.3, “Network Fault Protection in Action”, if rather than a network partition, nodes A and B fail, node C is the only node still running. Although node C is viable and could continue because the cluster was started with K-safety set to 2, if fault protection is enabled node C will shut itself down to avoid a partition.

In the worst case, if half the nodes of a cluster fail, the remaining nodes may actually shut themselves down under the special provisions for a network partition that splits a cluster into two equal parts. For example, consider the situation where a two node cluster with a k-safety value of one has network partition detection enabled. If one of the nodes fails (half the cluster), there is only a 50/50 chance the remaining node is the “blessed” node chosen to continue under these conditions. If the remaining node is *not* the chosen node, it will shut itself down to avoid a conflict, taking the database out of service in the process.

Because this situation — a 50/50 split — could result in either a network partition or a viable cluster shutting down, VoltDB recommends always using network partition detection and using clusters with an odd number of nodes. By using network partitioning, you avoid the dangers of a partition. By using an odd number of servers, you avoid even the possibility of a 50/50 split, whether caused by partitioning or node failures.

Chapter 12. Database Replication

There are times when it is useful to create a copy of a database. Not just a snapshot of a moment in time, but a live, constantly updated copy.

K-safety maintains redundant copies of partitions within a single VoltDB database, which helps protect the database cluster against individual node failure. Database replication also creates a copy. However, database replication creates and maintains a separate and distinct copy of the entire database.

Database replication can be used for:

- Offloading read-only workloads, such as reporting
- Maintaining a "hot standby" in case of failure
- Protecting against catastrophic events, often called disaster recovery


The next section, Section 12.1, “How Database Replication Works”, explains the principles behind database replication in VoltDB. Section 12.2, “Database Replication in Action” provides step-by-step instructions for establishing and managing database replication using the functions and features of VoltDB, including:

- Starting Replication
- Stopping Replication
- What to Do in Case of a Disaster
- Monitoring and Managing Replication

12.1. How Database Replication Works

Database replication involves duplicating the contents of one database cluster (known as the *master*) to another database cluster (known as the *replica*). The contents of the replica cluster are completely controlled by the master, which is why this arrangement is sometimes referred to as a *master/slave* relationship.

The replica database can be in the rack next to the master, in the next room, the next building, or another city entirely. The location depends upon your goals for replication. For example, if you are using replication for disaster recovery, geographic separation of the master and replica is required. If you are using replication for hot standby or offloading read-only queries, the physical location may not be important.

Figure 12.1. The Components of Database Replication

The process of retrieving completed transactions from the master and applying them to the replica is managed by a separate process called the Data Replication (DR) agent. The DR agent is critical to the replication process. It performs the following tasks:

- Initiates the replication, telling the master database to start queuing completed transactions and establishing a special client connection to the replica.
- POLLs and ACKs the completed transactions from the master database and recreates the transactions on the replica.
- Monitors the replication process, detects possible errors in the replica or delays in synchronizing the two clusters, and — when necessary — reports error conditions and cancels replication.

12.1.1. Starting Replication

Database Replication is easy to establish:

1. Any normal VoltDB database can be the master; you simply start the database as usual and the DR agent tells the master when it should start queuing completed transactions.
2. Next, you create the replica database. Again, this step is easy. However, rather than starting the database with the **create** or **recover** action, you start it with the **replica** action. This creates a read-only database that waits for the DR agent to contact it.
3. Finally, you start the DR agent, specifying the location of the master and replica databases.


Note that the DR agent can be located anywhere. However, the replication process is optimized for the DR agent to be co-located with the replica database (as shown in Figure 12.1, “The Components of Database Replication”). Communication between the DR agent and the master database is kept to a minimum to avoid bottlenecks; only write transactions are replicated and the messages between the master and the agent are compressed. Whereas the DR agent sends transactions to the replica using standard client invocations. Therefore, when distributing the database across a wide-area network (WAN), locating the DR agent near the replica is recommended.

12.1.2. Replication and Existing Databases

If data already exists in the master database when the DR agent starts replication, the master first creates a snapshot of the current contents and passes the snapshot to the DR agent so the master and the replica can

start from the same point. The master then queues and transmits all subsequent transactions to the agent, as shown in Figure 12.2, “Replicating an Existing Database”.

Figure 12.2. Replicating an Existing Database




12.1.3. Database Replication and Disaster Recovery

If unforeseen events occur that make the master database unreachable, database replication lets you replace the master with the replica and restore normal business operations with as little downtime as possible. You switch the replica from read-only to a fully functional database by promoting it to a master itself. To do this, perform the following steps:

1. Make sure the master is actually unreachable, because you do not want two live copies of the same database. If it is reachable but not functioning properly, be sure to shut it down.
2. Stop the DR agent, if it has not stopped already.
3. Promote the replica to a master using the **voltadmin promote** command.
4. Redirect the client applications to the new master database.

Figure 12.3, “Promoting the Replica” illustrates how database replication reduces the risk of major disasters by allowing the replica to replace the master if the master becomes unavailable.

Figure 12.3. Promoting the Replica



Once the master is offline and the replica is promoted to a master itself, the data is no longer being replicated. As soon as normal business operations have been re-established, it is a good idea to also re-establish replication. This can be done using any of the following options:

- If the original master database hardware can be restarted, take a snapshot of the current database (that is, the original replica), restore the snapshot on the original master and redirect client traffic back to the original. Replication can then be restarted using the original configuration.
- An alternative, if the original database hardware can be restarted but you do not want to (or need to) redirect the clients away from the current database, use the original master hardware to create a new replica — essentially switching the roles of the master and replica databases.
- If the original master hardware cannot be recovered effectively, create a new database cluster in a third location to use as a replica of the current database.

12.1.4. Database Replication and Completeness

It is important to note that, unlike K-safety where multiple copies of each partition are updated simultaneously, database replication involves shipping completed transactions from the master database to the replica. Because replication happens after the fact, there is no guarantee that the contents of the master and replica cluster are identical at any given point in time. Instead, the replica database 'catches up' with the master after the transactions are received and processed by the DR agent.

If the master cluster crashes, there is no guarantee that the DR agent has managed to retrieve all transactions that were queued on the master. Therefore, it is possible that some transactions that completed on the master are not reproduced on the replica.


The decision whether to promote the replica or wait for the master to return (and hopefully recover all transactions from the command log) is not an easy one. Promoting the replica and using it to replace the original master may involve losing one or more transactions. However, if the master cannot be recovered or cannot not be recovered quickly, waiting for the master to return can result in significant business loss or interruption.

Your own business requirements and the specific situation that caused the outage will determine which choice to make. However, database replication makes the choice possible and significantly eases the dangers of unforeseen events.

12.1.5. Database Replication and Read-only Clients

While database replication is occurring, the replica responds to write transactions (INSERT, UPDATE, and DELETE) from the DR agent only. Other clients can connect to the replica and use it for read-only transactions, including read-only ad hoc queries and system procedures. Any attempt to perform a write transaction from a client other than the DR agent returns an error.

There will always be some delay between a transaction completing on the master and being replayed on the replica. However, for read operations that do not require real-time accuracy (such as reporting), the replica can provide a useful source for offloading certain less-frequent, read-only transactions from the master.

Figure 12.4. Read-Only Access to the Replica

12.2. Database Replication in Action

The previous section explains the principles behind database replication. The following sections provide step-by-step instructions for setting up and managing replication using VoltDB.

All of the following examples use the same fictional servers to describe the replication process. The server used for the master cluster is called serverA; the server for the replica is serverB.

12.2.1. Starting Replication

It is easy to establish database replication with VoltDB. You can replicate any VoltDB database — there are no special requirements or configuration needed for the master database. It is also possible to begin replication of a new (empty) database or an existing database that already has content in it.

The steps to start replication are:

1. **Start the master database.**

You can either create a new database or use an existing database as the master. When starting the database, you can use either of the standard startup arguments: **create** or **recover**. For example:

```
$ voltdb create deployment deployment.xml \  
  catalog catalog.jar host serverA \  
  license license.xml
```

2. **Create a replica database.**

You create a replica database just as you would any other VoltDB database, except instead of specifying **create** as the startup action, you specify **replica**. For example:

```
$ voltdb replica deployment deployment.xml \  
  catalog catalog.jar host serverB \  
  license license.xml
```

Note that the replica database must:

- Start with the same catalog as the master database.

- Have the same configuration (that is, number of servers, sites per host, and K-safety value) as the master database.

If these settings do not match, the DR agent will report an error and fail to start in the next step.

3. Start the DR agent.

The DR agent is a separate process that can be run on any server that meets the hardware and software requirements for VoltDB. It is possible to run the agent on the same node as one of the master or replica cluster nodes. However, for best performance, it is recommended that the DR agent run on a separate, dedicated server located near the replica database.

To start the DR agent, use the `dragent` command specifying the IP address or hostname of a node from the master database and a node from the replica database as arguments to the command. For example:

```
$ dragent master serverA replica serverB
```

If the master or replica use ports other than the default, you can specify which port the DR agent should use as part of the server name. For example, the following command tells the agent to connect to the master starting at port 6666 and the replica on port 23232:

```
$ dragent master serverA:6666 replica serverB:23232
```

If you are using the Enterprise Manager to manage your databases, you can start the master database (Step 1) as you would normally, using the create, restore, or recover action. There is also a **replica** option on the Start Database dialog for creating a replica database (Step 2). The DR agent must be started by hand.

When the DR agent starts, it performs the following actions:

- Contacts both the master and replica databases.
- Verifies that the application catalogs match for the two databases.
- Verifies that the two clusters have the same number of unique partitions.
- Requests a snapshot from the master database. If data exists, the agent replays the snapshot on the replica.
- Begins to POLL and ACK the master database for completed transactions to be replayed on the replica.

12.2.2. Stopping Replication

If, for any reason, you wish to stop replication of a database, all you need to do is stop the DR agent process or the replica database. If either the agent or the replica database is not capable of processing the stream of transactions, the master will continue to queue completed transactions until the queue is full. At which point the master will abandon replication, delete the queue, and resume normal operation.

In other words, except for logging error messages explaining that replication has stopped, there is no outward change to the master cluster and no interruption of client activity. If you wish to shutdown replication in a more orderly fashion, you can:

1. Pause the master cluster, using the **voltadmin pause** command, to put the database in admin mode and stop client activity.
2. Once all transactions have passed through the DR agent to the replica (see Section 12.2.4.1, “Monitoring the Replication Process”), stop the DR agent process.

3. Stop the replica database, using **voltadmin shutdown** to perform an orderly shutdown.
4. Resume normal client operations on the master database, using **voltadmin resume**.

12.2.3. Promoting the Replica When the Master Becomes Unavailable

If the master database becomes unreachable for whatever reason (such as catastrophic system or network failure) and you choose to “turn on” the replica as a live database in its place, you use the **voltadmin promote** command to promote the replica to a fully active (writable) database. Specifically:

1. Stop the DR agent process. If not, the agent will report an error and stop after the following step.
2. Issue the **voltadmin promote** command on the replica database.

When you invoke **voltadmin promote**, the replica exits read-only mode and becomes a fully operational VoltDB database. For example, the following Linux shell command uses **voltadmin** to promote the replica node serverB:

```
$ voltadmin promote --host=serverB
```

12.2.4. Managing Database Replication

Database replication runs silently in the background, providing security against unexpected disruptions. Ideally, the replica will never be needed. But it is there just in case and the replication process is designed to withstand normal operational glitches. However, there are some conditions that can interrupt replication and it is important to be able to recognize and be able to respond to those situations, in order to ensure ongoing protection.

Both the master database and the DR agent maintain queues to handle fluctuations in the transmission of transactions. Network hiccups or a sudden increase of load on the master database can cause delays. Nodes on the master cluster may fail and rejoin (assuming K-safety). The queues help the replication process survive such interruptions.

If the problem persists for too long, it is possible for the queues to fill up, resulting in either the master or the DR agent (or both) canceling replication. When this happens, it is necessary to restart the replication process. The following sections explain how to monitor the replication process and how to respond to error conditions.

12.2.4.1. Monitoring the Replication Process

There are two ways to monitor the replication process:

- The DR agent provides a stream of informational messages concerning its status as part of its logs (displayed on the console by default).
- You can query the master database about its current replication queue using the @Statistics system procedure and the "DR" component type.

The DR agent logs information about the ongoing transmissions with the master and the replica. It also reports any issues communicating with the master and continues to retry until communication is re-established. If the agent encounters a problem it cannot recover from, it logs the error and the process stops. In this situation, you must restart replication from the beginning. (See Section 12.2.4.2, “Restarting Replication if an Error Occurs” for details.)

If you do not want the log messages displayed on the console, you can redirect them by providing an alternate Log4J configuration file. You specify the alternate configuration file with the environment variable LOG4J_CONFIG_PATH. For example, the following commands start the DR agent and specify an alternate log configuration file mylogconfig.xml in the current working directory:

```
$ export LOG4J_CONFIG_PATH="mylogconfig.xml"
$ dragent master serverA replica serverB
```

In addition to the DR agent logs, you can query the master database to determine the current state of its replication queues using the @Statistics system procedure. The "DR" keyword returns information about the amount of replication data currently in memory (waiting to be sent to the agent). One VoltTable reports the amount of memory used for queuing transactions and another reports on the current status of any snapshots (if any) waiting to be sent.

12.2.4.2. Restarting Replication if an Error Occurs

If an error does occur that causes replication to fail, you must restart replication from the beginning. In other words:

1. Stop the DR agent process, if it is not already stopped.
2. Shutdown and restart the replica database.
3. If the master database is not running, restart it.
4. Restart the DR agent.

Note that, if the master is still running, it does not need to be stopped and restarted. However, both the DR agent and the replica database *must* be restarted if any condition causes replication to fail. Situations that will require restarting replication include the following:

- If the replica database stops.
- If the master database stops.
- If the DR agent stops.
- If communication between the master and the DR agent is delayed to the point where the master cluster's replication queues overflow.
- If any transaction replayed on the replica fails. Note that only successfully completed transactions are sent to the replica. So if a transaction fails, the replica is no longer in sync with the master.
- If any transaction replayed on the replica returns a different result than received on the master. The results are hashed and compared. Just as all replicated transactions must succeed, they must produce the same results or the two databases are out of sync.

12.3. Using the Sample Applications to Demonstrate Replication

One way to familiarize yourself with replication is to try it with an existing application. VoltDB comes with several sample applications. You can use any of the samples to test or demonstrate replication.

The following sections show how to create a replicated database, using the voter application as an example. The first section explains how to use the Enterprise Manager for the demonstration and the second uses the VoltDB shell commands. Both examples assume you have three servers:

- ServerA as the master
- ServerB as the replica
- ServerC as the agent

It is also possible to perform this demonstration on two nodes by using ServerB for both the replica and the DR agent.

12.3.1. Replicating the Voter Sample Using the Enterprise Manager

First, using the command line, run the voter sample once to create the application catalog. Then, using the Enterprise Manager:

1. Create two new databases, *Voter Master* and *Voter Replica*, using the voter application catalog for both of them.
2. Add ServerA to the *Voter Master* database.
3. Add ServerB to the *Voter Replica* database.
4. Start both databases, using the **create** action for *Voter Master* and **create** and **replica** for *Voter Replica*.

From the command line on ServerC, start the DR agent using the following command:

```
$ dragent master serverA replica serverB
```

Finally, from the command line on ServerA, run the sample client application:

```
$ cd examples/voter
$ ./run.sh client
```

You should see the client inserts on the master database replicated on the replica. Note that you can also start the client application before the DR agent, to show that replication can be started on an existing, active database.

12.3.2. Replicating the Voter Sample Using the Command Line

In the current release, the scripts for running the sample applications do not add the necessary command line arguments for starting a master or replica database by default. However, you can use the **voltdb** convenience command to solve this problem:

1. On both ServerA and ServerB, run the voter sample once to build the application catalog:

```
$ cd examples/voter
$ ./run.sh catalog
```

2. On ServerA, use the **voltdb** command to start the master database:

```
$ voltdb catalog voter.jar deployment deployment.xml \
  host localhost license ../../voltdb/license.xml \
  create
```

3. On ServerB, use the **voltdb** command to start the replica database:

```
$ voltdb catalog voter.jar deployment deployment.xml \  
  host localhost license ../../voltdb/license.xml \  
  replica
```

4. On ServerC, use the **dragent** command to start the DR agent:

```
$ dragent master serverA replica serverB
```

5. On ServerB, start the voter client application:

```
$ ./run.sh client
```

Note that you can also start the client application (step #5) before the DR agent (step #4), to show that replication can be started on an existing, active database.

Chapter 13. Exporting Live Data

VoltDB is an in-memory, transaction processing database. It excels at managing large volumes of transactions in real-time.

However, transaction processing is often only one aspect of the larger business context and data needs to transition from system to system as part of the overall solution. The process of moving from one database to another as data moves through the system is often referred to as Extract, Transform, and Load (ETL). VoltDB supports ETL through the ability to selectively export data as it is committed to the database.

Exporting differs from save and restore (as described in Chapter 9, *Saving & Restoring a VoltDB Database*) in several ways:


- You only export selected data (as required by the business process)
- Export is an ongoing process rather than a one-time event
- The outcome of exporting data is that information is used by other business processes, not as a backup copy for restoring the database

The target for exporting data from VoltDB may be another database, a repository (such as a sequential log file), or a process (such as a system monitor or accounting system). No matter what the target, VoltDB helps automate the process for you. This chapter explains how to plan for and implement the exporting of live data using VoltDB.

13.1. Understanding Export

VoltDB lets you automate the export process by specifying certain tables in the schema as sources for export. At runtime, any data written to the specified tables is sent to the export *connector*, which manages the exchange of the updated information to a separate export process. The export client can run either locally on the database server as part of the database system or remotely as a separate application. Figure 13.1, “Overview of Export Process” illustrates the basic export procedure, where Tables B and D are specified as export tables.

Figure 13.1. Overview of Export Process



Note that you, as the application developer, do not need to modify the schema or the client application to turn exporting of live data on and off. The application's stored procedures insert data into the export-only tables; but it is the deployment file that determines whether export actually occurs at runtime.

When a stored procedure uses an SQL INSERT statement to write data into an export-only table, rather than storing that data in the database, it is handed off to the connector when the stored procedure successfully commits the transaction.¹ Export-only tables have several important characteristics:

- Export-only tables let you limit the export to only the data that is required. For example, in the preceding example, Table B may contain a subset of columns from Table A. Whenever a new record is written to Table A, the corresponding columns can be written to Table B for export to the remote database.
- Export-only tables let you combine fields from several existing tables into a single exported table. This technique is particularly useful if your VoltDB database and the target of the export have different schemas. The export-only table can act as a transformation of VoltDB data to a representation of the target schema.
- Export-only tables let you control *when* data is exported. Again, in the previous example, Table D might be an export-only table that is an exact replica of Table C. However, the records in Table C are updated frequently. The client application can choose to copy records from Table C to Table D only when all of the updates are completed and the data is finalized, significantly reducing the amount of data that must pass through the connector.

Of course, there are restrictions to export-only tables. Since they have no storage associated with them, they are for INSERT only. Any attempt to SELECT, UPDATE, or DELETE export-only tables will result in an error when the project is compiled.

13.2. Planning your Export Strategy

The important point when planning to export data, is deciding:

- What data to export
- When to export the data
- Whether to run the export client locally on the database servers or as a separate remote application

It is possible to export all of the data in a VoltDB database. You would do this by creating export-only replicas of all tables in the schema and writing to the export-only table whenever you insert into the normal table. However, this means the same number of transactions and volume of data that is being processed by VoltDB will be exported through the connector. There is a strong likelihood, given a high transaction volume, that the target database will not be able to keep up with the load VoltDB is handling. As a consequence you will usually want to be more selective about what data is exported when.

If you have an existing target database, the question of what data to export is likely decided for you (that is, you need to export the data matching the target's schema). If you are defining both your VoltDB database and your target at the same time, you will need to think about what information is needed "downstream" and create the appropriate export-only tables within VoltDB.

The second consideration is *when* to export the data. For tables that are not updated frequently, inserting the data to a complementary export-only table whenever data is inserted into the real table is the easiest and most practical approach. For tables that are updated frequently (hundreds or thousands of times a second) you should consider writing a copy of the data to an export-only table at an appropriate milestone.

The third consideration is where to run the export client. The recommended process is, where possible, to run the export client on the database server(s). Running the export client on the servers has two key advantages:

¹There is no guarantee on the latency of export between the connector and the export client. The export function is transactionally correct; no export occurs if the stored procedure rolls back and the export data is in the appropriate transaction order. But the flow of export data from the connector to the client is not synchronous with the completion of the transaction. There may be several seconds delay before the export data is available to the client.


- Export processing is distributed across the cluster, with each server exporting its own portion of the export workload. If you use a single remote export client, the client can become a bottleneck since it must process export data from all nodes of the cluster.
- Export processing starts and stops automatically. You do not need to manage and monitor the export client as a separate process.

Using the flight reservation system as an example, one aspect of the workflow not addressed by the application described in Chapter 3, *Designing Your VoltDB Application* is the need to archive information about the flights after takeoff. Changes to reservations (additions and cancellations) are important in real time. However, once the flight takes off, all that needs to be recorded (for billing purposes, say) is what reservations were active at the time.

In other words, the archiving database needs information about the customers, the flights, and the final reservations. According to the workload in Table 3.1, “Example Application Workload”, the customer and flight tables change infrequently. So data can be inserted into the export-only tables at the same time as the “live” flight and reservation tables. (It is a good idea to give the export-only copy of the table a meaningful name so its purpose is clear. In this example we identify the export-only tables with the `export_` prefix or, in the case of the reservation table which is not an exact copy, the `_final` suffix.)

The reservation table, on the other hand, is updated frequently. So rather than export all changes to a reservation to the export-only reservation table in real-time, a separate stored procedure is invoked when a flight takes off. This procedure copies the final reservation data to the export-only table and deletes the associated flight and reservation records from the VoltDB database. Figure 13.2, “Flight Schema with Export Table” shows the modified database schema with the added export-only tables, `EXPORT_FLIGHT`, `EXPORT_CUSTOMER`, and `RESERVATION_FINAL`.

Figure 13.2. Flight Schema with Export Table



This design adds a transaction to the VoltDB application, which is executed approximately once a second (when a flight takes off). However, it reduces the number of reservation transactions being exported from 1200 a second to less than 200 a second. These are the sorts of trade offs you need to consider when adding export functionality to your application.

13.3. Identifying Export Tables in the Schema

Once you have decide what data to export and define the appropriate tables in the schema, you are ready to identify them as export-only tables. As mentioned before, export-only tables are defined in the database schema just like any other table. So in the case of the flight application, we need to add the export tables to our schema. The following example illustrates (in bold) the addition of an export-only table for reservations with a subset of columns from the normal reservation table.

```
. . .  
  
CREATE TABLE Reservation (  
    ReserveID INTEGER UNIQUE NOT NULL,  
    FlightID INTEGER NOT NULL,  
    CustomerID INTEGER NOT NULL,  
    Seat VARCHAR(5) DEFAULT NULL,  
    Confirmed TINYINT DEFAULT '0',  
    PRIMARY KEY(ReserveID)  
);  
  
CREATE TABLE Reservation_final (  
    ReserveID INTEGER UNIQUE NOT NULL,  
    FlightID INTEGER NOT NULL,  
    CustomerID INTEGER NOT NULL,  
    Seat VARCHAR(5) DEFAULT NULL  
);  
  
. . .
```

Again, it is a good idea to distinguish export-only tables by their table name, so anyone reading the schema understands their purpose. Once you add the necessary tables to the schema, you then need to define them as export-only tables. You do this by adding an `EXPORT TABLE` statement for each table to the schema tags. For example:

```
EXPORT TABLE export_customer;  
EXPORT TABLE export_flight;  
EXPORT TABLE reservation_final;
```

If a table is not listed in an `EXPORT TABLE` statement, it is not exported. In the preceding example, the `export_customer`, `export_flight`, and `reservation_final` tables are identified as the tables that will be included in the export. In addition, since they are export-only tables, inserting data into these tables will have no effect if export is disabled in the deployment file.

You can also specify whether the export-only tables are partitioned or not using the `PARTITION TABLE` statement in the schema. For example, if an export table is a copy of a normal data table, it can be partitioned on the same column. However, partitioning is not necessary for export-only tables. Whether they are partitioned or "replicated", since no storage is associated with the export table, you can `INSERT` into the table in either a single-partitioned or multi-partitioned stored procedure. In either case, the export connector ensures that at least one copy of the tuple is written to the export stream.

13.4. Configuring Export in the Deployment File

The VoltDB connector creates packets of the serialized export data and then waits for an export client application to connect and request the packets. To enable the connector (and the export function) at runtime, you include the `<export>` tag in the deployment file.

```
<export enabled="true"/>
```

If you include the `<export>` tag without any attributes, you implicitly enable export. You can use the `enabled` attribute to explicitly enable or disable export.


13.5. How Export Works

The export connector implements a loosely coupled approach to extracting export data from a running VoltDB database. When export is enabled at runtime:

1. Insert operations to export-only tables are queued to the export connector.
2. If the export client is run on the database server, the client starts and links to the export connector. If the client is run remotely, it establishes a link to the connector through one of the standard TCP/IP ports (either the client or admin port). The client then issues POLL requests.
3. The connector responds to the POLL requests with the next queued data block (or an empty block if the queue is empty).
4. The client is then responsible for receiving the data and writing it to the appropriate destination.
5. Finally, the export client sends an ACK message acknowledging completion of the export (at which point the connector can remove it from the queue) before polling for the next data block.

Figure 13.3, “The Components of the Export Process” shows the interaction between the VoltDB database, the connector, and the export client.

Figure 13.3. The Components of the Export Process



The export function queues and passes data to the connector automatically. You do not need to do anything explicitly to start the connector; it starts and stops when the database starts and stops. The connector and the export client use a series of poll and ack requests to exchange the data over the TCP port.

The export client decides what is done with the data it receives from the connector. For example, one client writes the serialized data to a sequence of files while another could insert it into an analytic database.

When using a remote client, only one client can connect to the connector at a time. It is also important to note that the remote client must create connections to all nodes in the database cluster, since each node creates its own instance of the connector.

When running the export client on the server, each database server creates one instance each of the connector and the client, distributing the work across the cluster.

13.5.1. Export Overflow

For the export process to work, it is important that the connector and client keep up with the queue of exported information. If too much data gets queued to the connector by the export function without being fetched by the client, the VoltDB server process consumes increasingly large amounts of memory.

If the export client does not keep up with the connector and the data queue fills up, VoltDB starts writing overflow data in the export buffer to disk. This protects your database in several ways:

- If a remote export client fails, writing to disk helps VoltDB avoid consuming too much memory while waiting for the client to restart.

- If the database is stopped, the export data is retained across sessions. When the database restarts and the client reconnects, the connector will retrieve the overflow data and reinsert it in the export queue.

You can specify where VoltDB writes the overflow export data using the `<exportoverflow>` element in the deployment file. For example:

```
<paths>
  <voltdbroot path="/opt/voltdb/" />
  <exportoverflow path="/tmp/export/" />
</paths>
```

If you do not specify a path for export overflow, VoltDB creates a subfolder in the root directory (in the preceding example, `/opt/voltdb`). See Section 6.1.2, “Configuring Paths for Runtime Features” for more information about configuring paths in the deployment file.

13.5.2. Persistence Across Database Sessions

It is important to note that VoltDB only uses the disk storage for overflow data. However, you can force VoltDB to write all queued export data to disk by either calling the `@Quiesce` system procedure or by requesting a blocking snapshot. (That is, calling `@SnapshotSave` with the blocking flag set.) This means it is possible to perform an orderly shutdown of a VoltDB database and ensure all data (including export data) is saved with the following procedure:

1. Put the database into admin mode with the **`voltadmin pause`** command.
2. Perform a blocking snapshot with **`voltadmin save`**, saving both the database and any existing queued export data.
3. Shutdown the database with **`voltadmin shutdown`**.

You can then restore the database — and any pending export queue data — by starting the database in admin mode, restoring the snapshot, and then exiting admin mode.

13.6. Using the Export Clients

VoltDB comes with three export clients:

- Export to file
- Export to JDBC
- Export to Hadoop

As the name implies, the export-to-file client writes the exported data to local files, either as comma-separated or tab-delimited files. Similarly, the export-to-JDBC client writes data to a variety of possible destination databases through the JDBC protocol. Finally, the export-to-Hadoop client uses Sqoop, the SQL importer for Hadoop from Cloudera, to write the exported data to a Hadoop distributed file system.

Despite the different targets, the three export clients operate in the same way. The major difference is how you configure export, depending on whether you are running the client remotely or on the database server.

13.6.1. Running the Export Client on the Database Server

Where possible, running the export client on the database server is recommended because it simplifies the overall process, helps distribute the work, and avoids possible bottlenecks. Both the export-to-file and export-to-JDBC clients can be run on the server. Because of the complexities of configuring a Hadoop connection, the export-to-Hadoop client is available for remote operation only.

To enable export on the server, you include the `enabled` attribute to the `<export>` tag and the `<onserver>` tag as a child in the deployment file. You specify the client you wish to use as the argument to the `exportto` attribute of the `<onserver>` tag. Specify `"file"` for the export-to-file client or `"jdbc"` for the export-to-JDBC client. For example:

```
<export enabled="true">
  <onserver exportto="file">
    .
    .
    .
  </onserver>
</export>
```

When you enable server-side export processing, you must also configure the export client in the deployment file. You do this by specifying the configuration properties using the `<configuration>` tag enclosing one or more `<property>` tags. For example, the following XML code enables export to comma-separated (CSV) text files using the file prefix `"MyExport"`.

```
<export enabled="true">
  <onserver exportto="file">
    <configuration>
      <property name="type">csv</property>
      <property name="nonce">MyExport</property>
    </configuration>
  </onserver>
</export>
```

The properties that are allowed and/or required depend on the export client. Table 13.1, “File Export Client Properties” and Table 13.2, “JDBC Export Client Properties” list the required and optional properties for the export-to-file and export-to-JDBC clients, respectively.

Table 13.1. File Export Client Properties

Property	Allowable Values	Description
<code>type</code> [*]	csv, tsv	Specifies whether to create comma-separated (CSV) or tab-delimited (TSV) files,
<code>nonce</code> [*]	string	A unique prefix for the output files.
<code>outdir</code>	directory path	The directory where the files are created. If you do not specify an output path, the client writes the output files to the current default directory.
<code>period</code>	Integer	The frequency, in minutes, for "rolling" the output file. The default frequency is 60 minutes.
<code>binaryencoding</code>	hex, base64	Specifies whether VARBINARY data is encoded in hexadecimal or BASE64 format. The default is hexadecimal.
<code>dateformat</code>	format string	The format of the date used when constructing the output file names. You specify the date format as a Java SimpleDateFormat string. The default format is "yyyyMMddHHmmss".
<code>timezone</code>	string	The time zone to use when formatting the timestamp. Specify the time zone as a Java timezone identifier. The default is GMT.
<code>delimiters</code>	string	Specifies the delimiter characters for CSV output. The text string specifies four characters: the field delimiter, the enclosing character, the escape character, and the record delimiter.

Property	Allowable Values	Description
		To use special or non-printing characters (including the space character) encode the character as an HTML entity. For example "<" for the "less than" symbol.
batched	true, false	Specifies whether to store the output files in subfolders that are "rolled" according to the frequency specified by the period property. The subfolders are named according to the nonce and the timestamp, with "active-" prefixed to the subfolder currently being written.
skipinternals	true, false	Specifies whether to include six columns of VoltDB metadata (such as transaction ID and timestamp) in the output. If you specify skipinternals as "true", the output files contain only the exported table data.
with-schema	true, false	Specifies whether to write a JSON representation of each table's schema as part of the export. The JSON schema files can be used to ensure the appropriate datatype and precision is maintained if and when the output files are imported into another system.

* Required

Table 13.2. JDBC Export Client Properties

Property	Allowable Values	Description
jdbcurl*	connection string	The JDBC connection string, also known as the URL.
jdbcuser*	string	The username for accessing the target database.
jdbcpassword	string	The password for accessing the target database.
jdbcdriver	string	<p>The class name of the JDBC driver. The JDBC driver class must be accessible to the VoltDB process for the JDBC export process to work. Place the driver JAR files in the lib/extension directory where VoltDB is installed to ensure they are accessible at runtime.</p> <p>You do not need to specify the driver as a property value for several popular databases, including MySQL, Netezza, Oracle, PostgreSQL, and Vertica. However, you still must provide the driver JAR file.</p>
schema	string	The schema name for the target database. The use of the schema name is database specific. In some cases you must specify the database name as the schema. In other cases, the schema name is not needed and the connection string contains all the information necessary. See the documentation for the JDBC driver you are using for more information.
minpoolsize	integer	The minimum number of connections in the pool of connections to the target database. The default value is 10.
maxpoolsize	integer	The maximum number of connections in the pool. The default value is 100.
maxidletime	integer	The number of milliseconds a connection can be idle before it is removed from the pool. The default value is 60000 (one minute).

Property	Allowable Values	Description
maxstatement-cached	integer	The maximum number of statements cached by the connection pool. The default value is 50.
ignoregenerations	true, false	Specifies whether a unique ID for the generation of the database is included as part of the output table name(s). The generation ID changes each time a database restarts or the catalog is updated. The default is false.
skipinternals	true, false	Specifies whether to include six columns of VoltDB metadata (such as transaction ID and timestamp) in the output. If you specify skipinternals as true, the output contains only the exported table data. The default is false.

* Required

13.6.2. Running the Export Client Remotely

An alternative to running the export client on the database server(s) is to run an instance of the export client remotely. You can run either the export-to-file or export-to-Hadoop clients remotely. The export-to-JDBC client must be run on the database servers.

The major differences when running the export client remotely is that you specify the properties as options when starting the client process and you run only one instance of the client, which connects to all of the cluster nodes.

When you start an external export client, you specify the cluster nodes for the client to query for information (using the `--servers` argument). The client queries these nodes, one at a time, until it receives a response. Part of the response it receives is a description of the cluster, including a list of nodes and available ports. The client then creates connections to every node in the cluster using the port specified in the `--connect` argument (either the client port or the admin port).

Note that you don't have to specify all of the nodes of the cluster on the command line. You only have to specify one. The client then discovers the cluster configuration from the first node it reaches. However, you can specify multiple nodes in case one or more of the nodes is unavailable when the client starts.

Once the client connects to the cluster, it starts to poll and ack for export data. The client "decodes" the export stream from its serialized form into the appropriate datatypes for each column in the table. It then writes the data out to its appropriate target data form, whether files or a Hadoop distributed file system.

If the client loses connection to any of the nodes in the cluster (either because of a node failure or a shutdown), it disconnects from the cluster and repeats the initial discovery process, using the information it collected from the original connection. In other words, it will query every node in the cluster, one at a time, until it determines the new configuration. If the client cannot reach any of the nodes (for example, if the cluster is temporarily shut down) it will periodically retry the discovery process until the database cluster comes back online.

Once the cluster comes back, the client resumes export operations, picking up with the last data packet it received prior to the interruption. This allows the export process to continue without operator intervention even across network disruptions, node failures, and database sessions.

Both the export to file and export-to-Hadoop clients use the preceding process. The following sections describe each remote client and its operation in more detail.

13.7. The Export-to-JDBC Client

The export-to-JDBC client fetches the serialized data from the export connector and writes it, in batches, to another database through the standard JDBC (Java Database Connectivity) protocol. You configure the JDBC export client using the deployment file as described in Section 13.6.1, “Running the Export Client on the Database Server”.

When the Export-to-JDBC client opens the connection to the remote database, it first attempts to create tables in the remote database to match the VoltDB export-only tables by executing CREATE TABLE statements through JDBC. This is important to note because, it ensures there are suitable tables to receive the exported data. The tables are created using either the tables names from the VoltDB schema or (if you do not enable the ignoregenerations property) the table name prefixed by the database generation ID.

If the target database has existing tables that match the VoltDB export-only tables in both name and structure (that is, the number, order, and datatype of the columns), be sure the enable to ignoregenerations property in the export configuration to ensure that VoltDB uses those tables as the export target.

It is also important to note that the export-to-JDBC client exports data through JDBC in batches. That is, multiple INSERT instructions are passed to the remote client at a time, in approximately two megabyte batches. There are two consequences of the batching of export data:

- For many databases, such as Netezza, where there is a cost for individual invocations, batching reduces the performance impact on the receiving database and avoids unnecessary latency in the export processing.
- On the other hand, no matter what the target database, if a query fails for any reason the entire batch fails.

To avoid errors causing batch inserts to fail, it is strongly recommended that the target database not use unique indexes on the receiving tables that might cause constraint violations.

If any errors *do* occur when the Export-to-JDBC attempts to submit data to the remote database, the export client disconnects and then retries the connection. This process is repeated until the connection succeeds. If the connection does not succeed, the export client eventually reduces the retry rate to approximately every eight seconds.

13.8. The Export-to-File Client

The export-to-file client fetches the serialized data from the export connector and writes it out as text files (either comma or tab separated) to disk. For best performance and ease of use, you should run the export-to-file client on the database server(s) as described in Section 13.6.1, “Running the Export Client on the Database Server”.

However, it is possible to run the client as a remote process. Section 13.8.2, “The Export-to-File Client Command Line” describes the command line to run the client remotely.

13.8.1. Understanding the Export-to-File Client Output

When the export-to-file client receives export data, it de-serializes the content and writes it out to disk, one file per database table, “rolling” over to new files periodically. The filenames of the exported data are constructed from:

- A unique prefix (specified with `--nonce`)
- A unique value identifying the current version of the database catalog

- The table name
- A timestamp identifying when the file was started

While the file is being written, the file name also contains the prefix "active-". Once the file is complete and a new file started, the "active-" prefix is removed. Therefore, any export files without the prefix are complete and can be copied, moved, deleted, or post-processed as desired.

There are two main options when running the export-to-file client:

- The `--type` option lets you choose between comma-separated files (csv) or tab-delimited files (tsv).
- The `--batched` option tells the export client to group all of the files for one time period into a subfolder, rather than have all of the files in a single directory. In this case, when the export client "rolls" the files, it creates a new subfolder and it is the folder rather than the files that has the "active-" prefix appended to it.

Whatever options you choose, the order and representation of the content within the output files is the same. The export client writes a separate line of data for every INSERT it receives, including the following information:

- Six columns of metadata generated by the export connector. This information includes a transaction ID, a timestamp, a sequence number, the site and partition IDs, as well as an integer indicating the query type.
- The remaining columns are the columns of the database table, in the same order as they are listed in the database definition (DDL) file.

13.8.2. The Export-to-File Client Command Line

If you choose to run the export-to-file client remotely, VoltDB includes a shell command that lets you specify export properties, similar to those you can specify for server-based export. In its simplest form, the command looks something like the following:

```
$ exporttofile \  
    --connect client \  
    --servers myserver \  
    --nonce ExportData \  
    --type csv
```

The complete syntax of the command line is as follows:

```
$ exporttofile {arguments...}
```

```
$ exporttofile --help
```

The supported arguments are:

```
--servers {host-name[:port]} [...]
```

A comma separated list of host names or IP addresses to query.

```
--nonce {text}
```

The prefix to use for the files that the client creates. The client creates a separate file for every table that is exported, constructing a file name that includes a transaction ID, the nonce, the name of the table, a timestamp, and a file type specified by the `--type` argument.

`--connect {client | admin}`

The port to connect to. You specify the type of port (client or admin), not the port number.

`--type {csv | tsv}`

The type of files to create. You can specify either csv (for comma-separated files) or tsv (for tab-delimited files).

`--user {text}`

The username to use for authenticating to the VoltDB server(s). Required only if security is enabled for the database.

`--password {text}`

The password to use for authenticating to the VoltDB server(s). Required only if security is enabled for the database. If you specify a username but not a password, the export client prompts you for the password.

`--outdir {path}`

(Optional.) The directory where the output files are created. If you do not specify an output path, the client writes the output files to the current default directory.

`--period {integer}`

(Optional.) The frequency, in minutes, for "rolling" the output file. The default frequency is 60 minutes.

`--batched`

(Optional.) Store the output files in subfolders that are "rolled" according to the frequency specified by `--period`. The subfolders are named according to the nonce and the timestamp, with "active-" prefixed to the subfolder currently being written.

`--with-schema`

(Optional.) Writes a JSON representation of each table's schema as part of the export. The primary output files of the export-to-file client contain the exported data in rows, but do not identify the datatype of each column. The JSON schema files can be used to ensure the appropriate datatype and precision is maintained if and when the output files are imported into another system.

`--binaryencoding {base64 | hex}`

(Optional.) The format to use when encoding VARBINARY data for output. Binary data is encoded in either BASE64 or hexadecimal format. The default is hexadecimal.

`--delimiters {text}`

(Optional.) Alternate delimiter characters for the CSV output. The text string specifies four characters: the field delimiter, the enclosing character, the escape character, and the record delimiter. To use special or non-printing characters (including the space character) encode the character as an html entity. For example "<" for the "less than" symbol.

`--dateformat {format-string}`

(Optional.) The format of the date used when constructing the output file names. You specify the date format as a Java SimpleDateFormat string. The default format is "yyyyMMddHHmmss".

`--timezone {text}`

(Optional.) The time zone to use when formatting the timestamp. Specify the time zone as a Java timezone identifier. The default is GMT.

`--skipinternals`

(Optional.) Eliminates the six columns of VoltDB metadata (such as transaction ID and timestamp) from the output. If you specify `--skipinternals` the output files contain only the exported table data.

13.9. The Export-to-Hadoop Client

The export-to-Hadoop client fetches the serialized data from the export connector and — rather than writing it out as text files — exports it to the Hadoop distributed file system (hdfs) using the Sqoop import application from Cloudera.

To use the export-to-Hadoop client, you must have already installed and configured both Hadoop and Sqoop and started the Hadoop file system. The client uses the variable `HADOOP_HOME` to determine where Hadoop is installed and what file system to use as the target of the export. It then extracts and formats the exported data from the VoltDB connector and runs the Sqoop importer to read that data into Hadoop.

You start the export-to-Hadoop client using the Java command. However, it is important that all of the necessary JAR files for VoltDB, Hadoop, and Sqoop are in your class path. The easiest way to do this is using an Ant build script. But for demonstration purposes, the following example uses the export command to define `CLASSPATH`.

The command to start the export-to-Hadoop client looks something like the following:

```
$ V_PATH="/opt/voltdb/voltdb/*"
$ H_PATH="$HADOOP_HOME/*:$HADOOP_HOME/conf:$HADOOP_HOME/lib/*"
$ S_PATH="$SQOOP_HOME/*:$SQOOP_HOME/lib/*"
$ export CLASSPATH="$V_PATH:$H_PATH:$S_PATH"
$ java org.voltdb.hadoop.VoltDBSqoopExportClient \
    --connect client \
    --servers myserver \
    --nonce ExportData
```

13.9.1. The Export-to-Hadoop Client Command Line

The export-to-Hadoop client has a number of command line options that let you customize the export process to meet your needs. Many of the options are the same as for the export-to-file client. However, some options are specific to this client and allow you to control the Sqoop importer. In the following description the generic export client options are listed separately from the Sqoop-specific options.

The complete syntax of the command line is as follows:

```
$ java -classpath {path} \
    org.voltdb.hadoop.VoltDBSqoopExportClient \
    {arguments...}

$ java -classpath {path} \
    org.voltdb.hadoop.VoltDBSqoopExportClient \
    --help
```

The supported export client arguments are:

`--servers {host-name[:port]} [...]`

A comma separated list of host names or IP addresses to query.

`--nonce {text}`

The prefix to use for the directories that the client creates in Hadoop.

`--connect {client|admin}`

The port to connect to. You specify the type of port (client or admin), not the port number.

- `--user {text}`
The username to use for authenticating to the VoltDB server(s). Required only if security is enabled for the database.
- `--password {text}`
The password to use for authenticating to the VoltDB server(s). Required only if security is enabled for the database. If you specify a username but not a password, the export client prompts you for the password.
- `--period {integer}`
(Optional.) The frequency, in minutes, for "rolling" the output file. The default frequency is 60 minutes.
- `--outdir {path}`
(Optional.) The directory where temporary files are written as part of the export/import process.
- `--delimiters {text}`
(Optional.) Alternate delimiter characters for the CSV output. The text string specifies four characters: the field delimiter, the enclosing character, the escape character, and the record delimiter. To use special or non-printing characters (including the space character) encode the character as an html entity. For example "<" for the "less than" symbol.
- `--require-enclosed-output`
(Optional.) Specifies that all CSV fields, even numeric and null fields, are enclosed (in quotation marks, by default).
- `--http-port {integer}`
(Optional.) The http port for connecting to the Hadoop file system (port 8099 by default).
- `--skipinternals`
(Optional.) Eliminates the six columns of VoltDB metadata (such as transaction ID and timestamp) from the output. If you specify `--skipinternals` the output files contain only the exported table data.
- The following are supported Sqoop-specific arguments. These arguments are passed directly to the Sqoop importer interface and are documented in detail in the Sqoop documentation:
- `--hadoop-home {path}`
(Optional.) Overrides the value of the `HADOOP_HOME` environment variable. You must provide a valid Hadoop home directory, either by defining `HADOOP_HOME` or specifying the location with `--hadoop-home`.
- `--verbose`
(Optional.) Displays additional information during Sqoop processing.
- `--target-dir {path}`
(Optional.) The destination directory in HDFS.
- `--warehouse-dir {path}`
(Optional.) A parent directory in HDFS where separate folders are created for each table. The options `--target-dir` and `--warehouse-dir` are mutually exclusive.
- `--null-string {text}`
(Optional.) The string to use for null string values in the output.
- `--null-non-string {text}`
(Optional.) The string to use for null values in the output for all datatypes except strings.

Chapter 14. Logging and Analyzing Activity in a VoltDB Database

VoltDB uses Log4J, an open source logging service available from the Apache Software Foundation, to provide access to information about database events. By default, when using the VoltDB shell commands, the console display is limited to warnings, errors, and messages concerning the status of the current process. A more complete listing of messages (of severity INFO and above) is written to log files in the subfolder `/log`, relative to the user's current default location.

The advantages of using Log4J are:

- Logging is compiled into the code and can be enabled and configured at run-time.
- Log4J provides flexibility in configuring what events are logged, where, and the format of the output.
- By using Log4J in your client applications, you can integrate the logging and analysis of both the database and the application into a single consistent output stream.
- By using an open source logging service with standardized output, there are a number of different applications, such as Chainsaw, available for filtering and presenting the results.

Logging is important because it can help you understand the performance characteristics of your application, check for abnormal events, and ensure that the application is working as expected.

Of course, any additional processing and I/O will have an incremental impact on the overall database performance. To counteract any negative impact, Log4J gives you the ability to customize the logging to support only those events and servers you are interested in. In addition, when logging is not enabled, there is no impact to VoltDB performance. With VoltDB, you can even change the logging profile on the fly without having to shutdown or restart the database.

The following sections describe how to enable and customize logging of VoltDB using Log4J. This chapter is **not** intended as a tutorial or complete documentation of the Log4J logging service. For general information about Log4J, see the Log4J web site at <http://wiki.apache.org/logging-log4j/>.

14.1. Introduction to Logging

Logging is the process of writing information about application events to a log file, console, or other destination. Log4J uses XML files to define the configuration of logging, including three key attributes:

- **Where** events are logged. The destinations are referred to as *appenders* in Log4J (because events are appended to the destinations in sequential order).
- **What** events are logged. VoltDB defines named classes of events (referred to as *loggers*) that can be enabled as well as the severity of the events to report.
- **How** the logging messages are formatted (known as the *layout*),

14.2. Creating the Logging Configuration File

The following is an example of a Log4J configuration file:

```
<?xml version="1.0" encoding="UTF-8" ?>
```

```
<!DOCTYPE log4j:configuration SYSTEM "log4j.dtd">

<log4j:configuration xmlns:log4j="http://jakarta.apache.org/log4j/">

  <appender name="Async" class="org.apache.log4j.AsyncAppender">
    <param name="Blocking" value="true" />
    <appender-ref ref="Console" />
    <appender-ref ref="File" />
  </appender>

  <appender name="Console" class="org.apache.log4j.ConsoleAppender">
    <param name="Target" value="System.out" />
    <layout class="org.apache.log4j.TTCCLayout" />
  </appender>

  <appender name="File" class="org.apache.log4j.FileAppender">
    <param name="File" value="/tmp/voltdb.log" />
    <param name="Append" value="true" />
    <layout class="org.apache.log4j.TTCCLayout" />
  </appender>

  <logger name="AUTH">
    <!-- Print all VoltDB authentication messages -->
    <level value="trace" />
  </logger>

  <root>
    <priority value="debug" />
    <appender-ref ref="Async" />
  </root>
</log4j:configuration>
```

The preceding configuration file defines three destinations, or appenders, called *Async*, *Console*, and *File*. The appenders define the type of output (whether to the console, to a file, or somewhere else), the location (such as the file name), as well as the layout of the messages sent to the appender. See the log4J documentation for more information about layout.

Note that the appender *Async* is a superset of *Console* and *File*. So any messages sent to *Async* are routed to both *Console* and *File*. This is important because for logging of VoltDB, you should always use an asynchronous appender as the primary target to avoid the processing of the logging messages from blocking other execution threads.

The configuration file also defines a root class. The root class is the default logger and all loggers inherit the root definition. So, in this case, any messages of severity "debug" or higher are sent to the *Async* appender.

Finally, the configuration file defines a logger specifically for VoltDB authentication messages. The logger identifies the class of messages to log (in this case "AUTH"), as well as the severity ("trace"). VoltDB defines several different classes of messages you can log. Table 14.1, "VoltDB Components for Logging" lists the loggers you can invoke.

Table 14.1. VoltDB Components for Logging

Logger	Description
ADHOCPLANNERTHREAD	Execution of ad hoc queries

Logger	Description
AUTH	Authentication and authorization of clients
COMPILER	Interpretation of SQL in ad hoc queries
CONSOLE	Informational messages intended for display on the console
EXPORT	Exporting data
GC	Java garbage collection
HOST	Host specific events
NETWORK	Network events related to the database cluster
REJOIN	Node recovery and rejoin
SNAPSHOT	Snapshot activity
SQL	Execution of SQL statements
TM	Transaction management

14.3. Enabling Logging for VoltDB

Once you create your Log4J configuration file, you specify which configuration file to use by defining the variable `LOG4J_CONFIG_PATH` before starting the VoltDB database. For example:

```
$ LOG4J_CONFIG_PATH="$HOME/MyLog4jConfig.xml"
$ voltdb create \
    host localhost \
    catalog mycatalog.jar \
    deployment mydeployment.xml
```

14.4. Customizing Logging in the VoltDB Enterprise Manager

When using the VoltDB Enterprise Manager to manage your databases, the startup process is automated for you. There is no command line for specifying a Log4J configuration file.

Instead, the Enterprise Manager provides a Log4J properties file that is used to start each node in the cluster. You can change the logging configuration by modifying the properties file `server_log4j.properties` included in the `/management` subfolder of the VoltDB installation. The Enterprise Manager copies and uses this file to enable logging on all servers when it starts the database.

Note that the properties file used by the VoltDB Enterprise Manager is in a different format than the XML file used when configuring Log4J on the command line. However, both files let you configure the same logging attributes. In the case of the properties file, be sure to add your modifications to the end of the file so as not to interfere with the logging required by the Enterprise Manager itself.

14.5. Changing the Configuration on the Fly

Once the database has started, you can still start or reconfigure the logging without having to stop and restart the database. By calling the system procedure `@UpdateLogging` you can pass the configuration

XML to the servers as a text string. For any appenders defined in the new updated configuration, the existing appender is removed and the new configuration applied. Other existing appenders (those not mentioned in the updated configuration XML) remain unchanged.

Chapter 15. Using VoltDB with Other Programming Languages

VoltDB stored procedures are written in Java and the primary client interface also uses Java. However, that is not the only programming language you can use with VoltDB.

It is possible to have client interfaces written in almost any language. These client interfaces allow programs written in different programming languages to interact with a VoltDB database using native functions of the language. The client interface then takes responsibility for translating those requests into a standard communication protocol with the database server as described in the VoltDB wire protocol.

Some client interfaces are developed and packaged as part of the standard VoltDB distribution kit while others are compiled and distributed as separate client kits. As of this writing, the following client interfaces are available for VoltDB:

- C#
- C++
- Erlang
- Go
- Java (packaged with VoltDB)
- JDBC (packaged with VoltDB)
- JSON (packaged with VoltDB)
- Node.js
- PHP
- Python
- Ruby

The JSON client interface may be of particular interest if your favorite programming language is not listed above. JSON is a data format, rather than a programming interface, and the JSON interface provides a way for applications written in any programming language to interact with VoltDB via JSON messages sent across a standard HTTP protocol.

The following sections explain how to use the C++, JSON, and JDBC client interfaces.

15.1. C++ Client Interface

VoltDB provides a client interface for programs written in C++. The C++ client interface is available pre-compiled as a separate kit from the VoltDB web site, or in source format from the VoltDB github repository (<http://github.com/VoltDB/voltdb-client-cpp>). The following sections describe how to write VoltDB client applications in C++.

15.1.1. Writing VoltDB Client Applications in C++

When using the VoltDB client library, as with any C++ library, it is important to include all of the necessary definitions at the beginning of your source code. For VoltDB client applications, this includes defin-

itions for the VoltDB methods, structures, and datatypes as well as the libraries that VoltDB depends on (specifically, boost shared pointers). For example:

```
#include <boost/shared_ptr.hpp>
#include "Client.h"
#include "Table.h"
#include "TableIterator.h"
#include "Row.hpp"
#include "WireType.h"
#include "Parameter.hpp"
#include "ParameterSet.hpp"
#include <vector>
```

Once you have included all of the necessary declarations, there are three steps to using the interface to interact with VoltDB:

1. Create and open a client connection
2. Invoke stored procedures
3. Interpret the results

The following sections explain how to perform each of these functions.

15.1.2. Creating a Connection to the Database Cluster

Before you can call VoltDB stored procedures, you must create a client instance and connect to the database cluster. For example:

```
voltdb::ClientConfig config("myusername", "mypassword");
voltdb::Client client = voltdb::Client::create(config);
client.createConnection("myserver");
```

As with the Java client interface, you can create connections to multiple nodes in the cluster by making multiple calls to the **createConnection** method specifying a different IP address for each connection.

15.1.3. Invoking Stored Procedures

The C++ client library provides both a synchronous and asynchronous interface. To make a synchronous stored procedure call, you must declare objects for the parameter types, the procedure call itself, the parameters, and the response. Note that the datatypes, the procedure, and the parameters need to be declared in a specific order. For example:

```
/* Declare the number and type of parameters */
vector<voltdb::Parameter> parameterTypes(3);
parameterTypes[0] = voltdb::Parameter(voltdb::WIRE_TYPE_BIGINT);
parameterTypes[1] = voltdb::Parameter(voltdb::WIRE_TYPE_STRING);
parameterTypes[2] = voltdb::Parameter(voltdb::WIRE_TYPE_STRING);

/* Declare the procedure and parameter structures */
voltdb::Procedure procedure("AddCustomer", parameterTypes);
voltdb::ParameterSet* params = procedure.params();

/* Declare a client response to receive the status and return values */
```

```
boost::shared_ptr<voltdb::InvocationResponse> response;
```

Once you instantiate these objects, you can reuse them for multiple calls to the stored procedure, inserting different values into *params* each time. For example:

```
params->addInt64(13505).addString("William").addString("Smith");
response = client->invoke(procedure);
params->addInt64(13506).addString("Mary").addString("Williams");
response = client->invoke(procedure);
params->addInt64(13507).addString("Bill").addString("Smythe");
response = client->invoke(procedure);
```

15.1.4. Invoking Stored Procedures Asynchronously

To make asynchronous procedure calls, you must also declare a callback structure and method that will be used when the procedure call completes.

```
class AsyncCallback : public voltdb::ProcedureCallback
{
public:
    bool callback
        (boost::shared_ptr<voltdb::InvocationResponse> response)
        throw (voltdb::Exception)
    {
        /*
         * The work of your callback goes here...
         */
    }
}
```

Then, when you go to make the actual stored procedure invocation, you declare an callback instance and invoke the procedure, using both the procedure structure and the callback instance:

```
boost::shared_ptr<AsyncCallback> callback(new AsyncCallback());
client->invoke(procedure, callback);
```

Note that the C++ interface is single-threaded. The interface is not thread-safe and you should not use instances of the client, client response, or other client interface structures from within multiple concurrent threads. Also, the application must release control occasionally to give the client interface an opportunity to issue network requests and retrieve responses. You can do this by calling either the `run()` or `runOnce()` methods.

The `run()` method waits for and processes network requests, responses, and callbacks until told not to. (That is, until a callback returns a value of false.)

The `runOnce()` method processes any outstanding work and then returns control to the client application.

In most applications, you will want to create a loop that makes asynchronous requests and then calls `runOnce()`. This allows the application to queue stored procedure requests as quickly as possible while also processing any incoming responses in a timely manner.

Another important difference when making stored procedure calls asynchronously is that you must make sure all of the procedure calls complete before the client connection is closed. The client objects destructor automatically closes the connection when your application leaves the context or scope within which the

client is defined. Therefore, to make sure all asynchronous calls have completed, be sure to call the *drain* method until it returns true before leaving your client context:

```
while (!client->drain()) {}
```

15.1.5. Interpreting the Results

Both the synchronous and asynchronous invocations return a client response object that contains both the status of the call and the return values. You can use the status information to report problems encountered while running the stored procedure. For example:

```
if (response->failure())
{
    cout << "Stored procedure failed. " << response->toString();
    exit(-1);
}
```

If the stored procedure is successful, you can use the client response to retrieve the results. The results are returned as an array of VoltTable structures. Within each VoltTable object you can use an iterator to walk through the rows. There are also methods for retrieving each datatype from the row. For example, the following example displays the results of a single VoltTable containing two strings in each row:

```
/* Retrieve the results and an iterator for the first volttable */
vector<boost::shared_ptr<voltdb::Table> > results = response->results();
voltdb::TableIterator iterator = results[0]->iterator();

/* Iterate through the rows */
while (iterator.hasNext())
{
    voltdb::Row row = iterator.next();
    cout << row.getString(0) << ", " << row.getString(1) << endl;
}
```

15.2. JSON HTTP Interface

JSON (JavaScript Object Notation) is not a programming language; it is a data format. The JSON "interface" to VoltDB is actually a web interface that the VoltDB database server makes available for processing requests and returning data in JSON format.

The JSON interface lets you invoke VoltDB stored procedures and receive their results through HTTP requests. To invoke a stored procedure, you pass VoltDB the procedure name and parameters as a querystring to the HTTP request, using either the GET or POST method.

Although many programming languages provide methods to simplify the encoding and decoding of JSON strings, you still need to understand the data structures that are created. So if you are not familiar with JSON encoding, you may want to read more about it at <http://www.json.org>.

15.2.1. How the JSON Interface Works

To use the VoltDB JSON interface, you must first enable JSON in the deployment file. You do this by adding the following tags to the deployment file:

```
<httpd>
  <jsonapi enabled="true"/>
</httpd>
```

With JSON enabled, when a VoltDB database starts it opens port 8080¹ on the local machine as a simple web server. Any HTTP requests sent to the location /api/1.0/ on that port are interpreted as requests to run a stored procedure. The structure of the request is:

URL	http://<server>:8080/api/1.0/
Arguments	Procedure=<procedure-name> Parameters=<procedure-parameters> User=<username for authentication> Password=<password for authentication> Hashedpassword=<Hashed password for authentication> admin=<true false> jsonp=<function-name>

The arguments can be passed either using the GET or the POST method. For example, the following URL uses the GET method (where the arguments are appended to the URL) to execute the system procedure @SystemInformation on the VoltDB database running on node voltsvr.mycompany.com:

```
http://voltsvr.mycompany.com:8080/api/1.0/?Procedure=@SystemInformation
```

Note that only the Procedure argument is required. You can authenticate using the User and Password (or Hashedpassword) arguments if security is enabled for the database. Use Password to send the password as plain text or Hashedpassword to send the password as a SHA-1 encoded string. (The hashed password must be a 40-byte hex-encoding of the 20-byte SHA-1 hash.)²

You can also include the parameters on the request. However, it is important to note that the parameters — and the response returned by the stored procedure — are JSON encoded. The parameters are an array (even if there is only one element to that array) and therefore must be enclosed in square brackets.

The admin argument specifies whether the request is submitted on the standard client port (the default) or the admin port (when you specify admin=true). If the database is in admin mode, you must submit requests over the admin port or else the request is rejected by the server.

The admin port should be used for administrative tasks only. Although all stored procedures can be invoked through the admin port, using the admin port through JSON is far less efficient than using the client port. All admin mode requests to JSON are separate synchronous requests; whereas calls to the normal client port are asynchronous through a shared session.

The jsonp argument is provided as a convenience for browser-based applications (such as Javascript) where cross-domain browsing is disabled. When you include the jsonp argument, the entire response is wrapped as a function call using the function name you specify. Using this technique, the response is a complete and valid Javascript statement and can be executed to create the appropriate language-specific object. For example, calling the @Statistics system procedure in Javascript using the jQuery library looks like this:

```
$.getJSON( 'http://myserver:8080/api/1.0/?Procedure=@Statistics' +
          '&Parameters=[ "MANAGEMENT", 0 ]&jsonp=?' ,
          { } , MyCallback ) ;
```

Perhaps the best way to understand the JSON interface is to see it in action. If you build and start the Hello World example application that is provided in the VoltDB distribution kit (including the client that loads

¹You can specify an alternate port for the JSON interface when you start the VoltDB server by including the port number as an attribute of the <httpd> tag in the deployment file. For example: <httpd port="{port-number}">.

²Hashing the password stops the text of your password from being detectable from network traffic. However, it does not make the database access any more secure. To secure the transmission of credentials and data between client applications and VoltDB, use an SSL proxy server in front of the database servers.

data into the database), you can then open a web browser and connect to the local system through port 8080, to retrieve the French translation of "Hello World". For example:

```
http://localhost:8080/api/1.0/?Procedure=Select&Parameters=[ "French" ]
```

The resulting display is the following:

```
{ "status":1, "appstatus":-128, "statusstring":null, "appstatusstring":null,
  "exception":null, "results":[ { "status":-128, "schema":[ { "name":"HELLO",
    "type":9 }, { "name":"WORLD", "type":9 } ], "data":[ [ "Bonjour", "Monde" ] ] } ] }
```

As you can see, the results (which are a JSON-encoded string) are not particularly easy to read. But then, the JSON interface is not really intended for human consumption. Its real purpose is to provide a generic interface accessible from almost any programming language, many of which already provide methods for encoding and decoding JSON strings and interpreting their results.

15.2.2. Using the JSON Interface from Client Applications

The general process for using the JSON interface from within a program is:

1. Encode the parameters for the stored procedure as a JSON-encoded string
2. Instantiate and execute an HTTP request, passing the name of the procedure and the parameters as arguments using either GET or POST.
3. Decode the resulting JSON string into a language-specific data structure and interpret the results.

The following are examples of invoking the Hello World Insert stored procedure from several different languages. In each case, the three arguments (the name of the language and the words for "Hello" and "World") are encoded as a JSON string.

PHP

```
// Construct the procedure name, parameter list, and URL.

$voltdbserver = "http://myserver:8080/api/1.0/";
$proc = "Insert";
$a = array("Croatian", "Pozdrav", "Svijet");
$params = json_encode($a);
$params = urlencode($params);
$querystring = "Procedure=$proc&Parameters=$params";

// create a new cURL resource and set options
$ch = curl_init();
curl_setopt($ch, CURLOPT_URL, $voltdbserver);
curl_setopt($ch, CURLOPT_HEADER, 0);
curl_setopt($ch, CURLOPT_FAILONERROR, 1);
curl_setopt($ch, CURLOPT_POST, 1);
curl_setopt($ch, CURLOPT_POSTFIELDS, $querystring);
curl_setopt($ch, CURLOPT_RETURNTRANSFER, true);

// Execute the request
$resultstring = curl_exec($ch);
```

Python

```
import urllib
import urllib2
import json

# Construct the procedure name, parameter list, and URL.
url = 'http://myserver:8080/api/1.0/'
voltparams = json.dumps(["Croatian", "Pozdrav", "Svijet"])
httpparams = urllib.urlencode({
    'Procedure': 'Insert',
    'Parameters' : voltparams
})
print httpparams
# Execute the request
data = urllib2.urlopen(url, httpparams).read()

# Decode the results
result = json.loads(data)
```

Perl

```
use LWP::Simple;

my $server = 'http://myserver:8080/api/1.0/';

# Insert "Hello World" in Croatian
my $proc = 'Insert';
my $params = '["Croatian", "Pozdrav", "Svijet"]';
my $url = $server . "?Procedure=$proc&Parameters=$params";
my $content = get $url;
die "Couldn't get $url" unless defined $content;
```

C#

```
using System;
using System.Text;
using System.Net;
using System.IO;

namespace hellovolt
{
    class Program
    {
        static void Main(string[] args)
        {
            string VoltDBServer = "http://myserver:8080/api/1.0/";
            string VoltDBProc = "Insert";
            string VoltDBParams = "[\"Croatian\", \"Pozdrav\", \"Svijet\"]";
            string Url = VoltDBServer + "?Procedure=" + VoltDBProc
                + "&Parameters=" + VoltDBParams;

            string result = null;
```

```

        WebResponse response = null;
        StreamReader reader = null;

        try
        {
            HttpWebRequest request = (HttpWebRequest)WebRequest.Create(Url);
            request.Method = "GET";
            response = request.GetResponse();
            reader = new StreamReader(response.GetResponseStream(), Encoding.UTF8 );
            result = reader.ReadToEnd();
        }
        catch (Exception ex)

        {
            // handle error
            Console.WriteLine( ex.Message );
        }
        finally
        {
            if (reader != null) reader.Close();
            if (response != null) response.Close();
        }
    }
}
}

```

15.2.3. How Parameters Are Interpreted

When you pass arguments to the stored procedure through the JSON interface, VoltDB does its best to map the data to the datatype required by the stored procedure. This is important to make sure partitioning values are interpreted correctly.

For integer values, the JSON interface maps the parameter to the smallest possible integer type capable of holding the value. (For example, BYTE for values less than 128). Any values containing a decimal point are interpreted as DOUBLE.

String values (those that are quoted) are handled in several different ways. If the stored procedure is expecting a BIGDECIMAL, the JSON interface will try to interpret the quoted string as a decimal value. If the stored procedure is expecting a TIMESTAMP, the JSON interface will try to interpret the quoted string as a JDBC-encoded timestamp value. (You can alternately pass the argument as an integer value representing the number of microseconds from the epoch.) Otherwise, quoted strings are interpreted as a string datatype.

Table 15.1, “Datatypes in the JSON Interface” summarizes how to pass different datatypes in the JSON interface.

Table 15.1. Datatypes in the JSON Interface

Datatype	How to Pass	Example
Integers (Byte, Short, Integer, Long)	An integer value	12345
DOUBLE	A value with a decimal point	123.45

Datatype	How to Pass	Example
BIGDECIMAL	A quoted string containing a value with a decimal point	"123.45"
TIMESTAMP	Either an integer value or a quoted string containing a JDBC-encoded date and time	12345 "2010-07-01 12:30:21"
String	A quoted string	"I am a string"

15.2.4. Interpreting the JSON Results

Making the request and decoding the result string are only the first steps. Once the request is completed, your application needs to interpret the results.

When you decode a JSON string, it is converted into a language-specific structure within your application, composed of objects and arrays. If your request is successful, VoltDB returns a JSON-encoded string that represents the same ClientResponse object returned by calls to the callProcedure method in the Java client interface. Figure 15.1, “The Structure of the VoltDB JSON Response” shows the structure of the object returned by the JSON interface.

Figure 15.1. The Structure of the VoltDB JSON Response

```
{
  appstatus      (integer, boolean)
  appstatusstring (string)
  exception      (integer)
  results        (array)
  [
    [
      {
        data      (array)
        [
          (any type)
        ]
        schema    (array)
        [
          name    (string)
          type     (integer, enumerated)
        ]
        status    (integer, boolean)
      }
    ]
  ]
  status         (integer)
  statusstring   (string)
}
```

The key components of the JSON response are the following:

appstatus	Indicates the success or failure of the stored procedure. If <i>appstatus</i> is false, <i>appstatusstring</i> contains the text of the status message.
results	An array of objects representing the data returned by the stored procedure. This is an array of VoltTable objects. If the stored procedure does not return a value (i.e. is void or null), then <i>results</i> will be null.
data	Within each VoltTable object, <i>data</i> is the array of values.
schema	Within each VoltTable, object <i>schema</i> is an array of objects with two elements: the name of the field and the datatype of that field (encoded as an enumerated integer value).

status Indicates the success or failure of the VoltDB server in its attempt to execute the stored procedure. The difference between *appstatus* and *status* is that if the server cannot execute the stored procedure, the status is returned in *status*, whereas if the stored procedure can be invoked, but a failure occurs within the stored procedure itself (such as a SQL constraint violation), the status is returned in *appstatus*.

It is possible to create a generic procedure for testing and evaluating the result values from any VoltDB stored procedure. However, in most cases it is far more expedient to evaluate the values that you know the individual procedures return.

For example, again using the Hello World example that is provided with the VoltDB software, it is possible to use the JSON interface to call the Select stored procedure and return the values for "Hello" and "World" in a specific language. Rather than evaluate the entire results array (including the name and type fields), we know we are only receiving one VoltTable object with two string elements. So we can simplify the code, as in the following python example:

```
import urllib
import urllib2
import json
import pprint

# Construct the procedure name, parameter list, and URL.
url = 'http://localhost:8080/api/1.0/'
voltparams = json.dumps(["French"])
httpparams = urllib.urlencode({
    'Procedure': 'Select',
    'Parameters' : voltparams
})

# Execute the request
data = urllib2.urlopen(url, httpparams).read()

# Decode the results
result = json.loads(data)

# Get the data as a simple array and display them
foreignwords = result[u'results'][0][u'data'][0]

print foreignwords[0], foreignwords[1]
```

15.2.5. Error Handling using the JSON Interface

There are a number of different reasons why a stored procedure request using the JSON interface may fail: the VoltDB server may be unreachable, the database may not be started yet, the stored procedure name may be misspelled, the stored procedure itself may fail... When using the standard Java client interface, these different situations are handled at different times. (For example, server and database access issues are addressed when instantiating the client, whereas stored procedure errors can be handled when the procedures themselves are called.) The JSON interface simplifies the programming by rolling all of these activities into a single call. But you must be more organized in how you handle errors as a consequence.

When using the JSON interface, you should check for errors in the following order:

1. First check to see that the HTTP request was submitted without errors. How this is done depends on what language-specific methods you use for submitting the request. In most cases, you can use the appropriate programming language error handlers (such as try-catch) to catch and interpret HTTP request errors.

2. Next check to see if VoltDB successfully invoked the stored procedure. You can do this by verifying that the HTTP request returned a valid JSON-encoded string and that its *status* is set to true.
3. If the VoltDB server successfully invoked the stored procedure, then check to see if the stored procedure itself succeeded, by checking to see if *appstatus* is true.
4. Finally, check to see that the results are what you expect. (For example, that the *data* array is non-empty and contains the values you need.)

15.3. JDBC Interface

JDBC (Java Database Connectivity) is a programming interface for Java programmers that abstracts database specifics from the methods used to access the data. JDBC provides standard methods and classes for accessing a relational database and vendors then provide JDBC drivers to implement the abstracted methods on their specific software.

VoltDB provides a JDBC driver for those who would prefer to use JDBC as the data access interface. The VoltDB JDBC driver supports ad hoc queries, prepared statements, calling stored procedures, and methods for examining the metadata that describes the database schema.

15.3.1. Using JDBC to Connect to a VoltDB Database

The VoltDB driver is a standard class within the VoltDB software jar. To load the driver you use the `Class.forName` method to load the class `org.voltdb.jdbc.Driver`.

Once the driver is loaded, you create a connection to a running VoltDB database server by constructing a JDBC url using the "jdbc:" protocol, followed by "voltdb://", the server name, a colon, and the port number. In other words, the complete JDBC connection url is "jdbc:voltdb://{server}:{port}".

For example, the following code loads the VoltDB JDBC driver and connects to the server `svr1` using the default client port:

```
Class.forName("org.voltdb.jdbc.Driver");
Connection c = DriverManager.getConnection("jdbc:voltdb://svr1:21212");
```

15.3.2. Using JDBC to Query a VoltDB Database

Once the connection is made, you use the standard JDBC classes and methods to access the database. (See the JDBC documentation at <http://download.oracle.com/javase/6/docs/technotes/guides/jdbc> for details.) Note, however, when running the JDBC application, you must make sure the VoltDB software jar is in the Java classpath or the application will not be able to find the driver class.

The following is a complete example that uses JDBC to access the Hello World tutorial described in *Getting Started With VoltDB* and executes both an ad hoc query and a call to the VoltDB stored procedure, `Select`.

```
import java.sql.*;
import java.io.*;

public class JdbcDemo {

    public static void main(String[] args) {

        String driver = "org.voltdb.jdbc.Driver";
        String url = "jdbc:voltdb://localhost:21212";
```



```
String sql = "SELECT dialect FROM helloworld";

try {
    // Load driver. Create connection.
    Class.forName(driver);
    Connection conn = DriverManager.getConnection(url);

    // create a statement
    Statement query = conn.createStatement();
    ResultSet results = query.executeQuery(sql);
    while (results.next()) {
        System.out.println("Language is " + results.getString(1));
    }

    // call a stored procedure
    CallableStatement proc = conn.prepareCall("{call Select(?)}");
    proc.setString(1, "French");
    results = proc.executeQuery();
    while (results.next()) {
        System.out.printf("%s, %s!\n", results.getString(1),
                           results.getString(2));
    }

    //Close statements, connections, etc.
    query.close();
    proc.close();
    results.close();
    conn.close();

} catch (Exception e) {
    e.printStackTrace();
}
}
```

Appendix A. Supported SQL DDL Statements

This appendix describes the subset of the SQL Data Definition Language (DDL) that VoltDB supports when defining the schema for a VoltDB database. VoltDB also supports extensions to the standard syntax to allow for the declaration of stored procedures and partitioning information related to tables and procedures.

The following sections are not intended as a complete description of the standard SQL DDL. Instead, they summarize the subset of standard SQL DDL statements that are allowed in a VoltDB schema definition and any exceptions, extensions, or limitations that application developers should be aware of.

The supported standard SQL DDL statements are:

- CREATE INDEX
- CREATE TABLE
- CREATE VIEW

The supported VoltDB-specific extensions for declaring stored procedures and partitioning are:

- CREATE PROCEDURE AS
- CREATE PROCEDURE FROM CLASS
- CREATE ROLE
- EXPORT TABLE
- PARTITION PROCEDURE
- PARTITION TABLE

CREATE INDEX

CREATE INDEX — Creates an index for faster access to a table.

Syntax

```
CREATE [UNIQUE] INDEX index-name ON table-name ( index-column [...])
```

Description

Creating an index on a table makes read access to the table faster when using the index as a key. Note that VoltDB creates an index automatically when you specify a primary key in the CREATE TABLE statement.

When you specify that the index is UNIQUE, VoltDB constrains the table to at most one row for each index value. If an INSERT or UPDATE statement attempts to create a row where all the index column values match an existing indexed row, the statement fails. Because the uniqueness constraint is applied to the current partition, to ensure global uniqueness for partitioned tables a unique index must contain the partitioning column for the table.

The indexed items (*index-column*) are either columns of the specified table or numeric expressions, including functions, based on the table. For example, the following statements index a table based on the calculated area and its distance from a set location:

```
CREATE INDEX areaofplot ON plot (width * height);
CREATE INDEX distancefrom49 ON plot ( ABS(latitude - 49) );
```

By default, VoltDB creates a tree index. Tree indexes provide the best general performance for a wide range of operations, including exact value matches and queries involving a range of values, such as SELECT ... WHERE Score > 1 AND Score < 10.

If an index is used exclusively for exact matches (such as SELECT ... WHERE MyHashColumn = 123), it is possible to create a hash index instead. To create a hash index, include the string "hash" as part of the index name.

CREATE PROCEDURE AS

CREATE PROCEDURE AS — Defines a stored procedure composed of a SQL query.

Syntax

```
CREATE PROCEDURE procedure-name [ALLOW role-name [...]] AS sql-statement
```

Description

You must declare stored procedures as part of the schema to make them accessible at runtime. The declared procedures are evaluated and included in the application catalog when you compile the database schema.

Use CREATE PROCEDURE AS when declaring simple stored procedures consisting of a single SQL query statement. The SQL statement can contain question marks (?) as placeholders that are filled in at runtime with the arguments to the procedure call.

The procedure name must follow the naming conventions for Java class names. For example, the name is case-sensitive and cannot contain any white space.

If security is enabled at runtime, only those roles named in the ALLOW clause have permission to invoke the procedure. If security is not enabled at runtime, the ALLOW clause is ignored and all users have access to the stored procedure.

CREATE PROCEDURE FROM CLASS

CREATE PROCEDURE FROM CLASS — Defines a stored procedure associated with a Java class.

Syntax

```
CREATE PROCEDURE [ALLOW role-name [...]] FROM CLASS class-name
```

Description

You must declare stored procedures to make them accessible at runtime. The declared procedures are evaluated and included in the application catalog when you compile the database schema.

If security is enabled at runtime, only those roles named in the ALLOW clause have permission to invoke the procedure. If security is not enabled at runtime, the ALLOW clause is ignored and all users have access to the stored procedure.

Use CREATE PROCEDURE FROM CLASS when adding user-defined stored procedures written in Java. The *class-name* is the name of the Java class. This class must be accessible from the classpath argument used when compiling the application catalog.

CREATE ROLE

CREATE ROLE — Defines a role and the permissions associated with that role.

Syntax

```
CREATE ROLE role-name [WITH permission [...]]
```

Description

The CREATE ROLE statement defines a named role that can be used to assign access rights to specific procedures and functions. When security is enabled in the deployment file, the permissions assigned in the CREATE ROLE and CREATE PROCEDURE statements specify which users can access which functions.

Use the CREATE PROCEDURE statement to assign permissions to named roles for accessing specific stored procedures. The CREATE ROLE statement lets you assign certain generic permissions. The permissions that can be assigned by the WITH clause are:

ADHOC	Allows access to ad hoc queries (through the @AdHoc system procedure and sqlcmd command)
DEFAULT-PROC	Allows access to the default procedures for all tables
EXPORT	Allows access to the export connector for export clients
SYSPROC	Allows access to all system procedures

The generic permissions are denied by default. So you must explicitly enable them for those roles that need them. For example, if users assigned to the "interactive" role need to run ad hoc queries, you must explicitly assign that permission in the CREATE ROLE statement:

```
CREATE ROLE interactive WITH adhoc;
```

Also note that the permissions are additive. So if a user is assigned to one role that allows access to adhoc but not sysproc, but that user also is assigned to another role that allows sysproc, the user has both permissions.

- Each column has a maximum size of one megabyte and the sum of the actual content in the columns for any given row cannot exceed two megabytes.
- If you intend to use a column to partition a table, that column cannot contain null values. You must specify NOT NULL in the definition of the column or VoltDB issues an error when compiling the schema.
- When you specify a primary key, by default VoltDB creates a tree index. You can explicitly create a hash index by including the string "hash" as part of the index name. For example, the following declaration creates a hash index, `Version_Hash_Idx`, of three numeric columns.

```
CREATE TABLE Version (  
    Major SMALLINT NOT NULL,  
    Minor SMALLINT NOT NULL,  
    baselevel INTEGER NOT NULL,  
    ReleaseDate TIMESTAMP,  
    CONSTRAINT Version_Hash_Idx PRIMARY KEY  
        (Major, Minor, Baselevel)  
);
```

See the description of CREATE INDEX for more information on the difference between hash and tree indexes.

- For integer and floating-point datatypes, the largest possible negative value is reserved by VoltDB and interpreted as null.
- The VARBINARY datatype provides variable storage for arbitrary strings of binary data and operates similarly to VARCHAR strings. You assign byte arrays to a VARBINARY column when passing in variables, or you can use a hexadecimal string for assigning literal values in the SQL statement. However, VARBINARY columns cannot be used in indexes or in conditional comparisons (such as in SELECT ... WHERE statements).
- The VoltDB Timestamp datatype is a long integer representing the number of microseconds since the epoch. Two important points to note about this timestamp:
 - The VoltDB Timestamp is not the same as the Java Timestamp datatype or traditional Linux time measurements, which are measured in milliseconds rather than microseconds. Appropriate conversion is needed when casting values between a VoltDB timestamp and other timestamp datatypes.
 - The VoltDB Timestamp is interpreted as a Greenwich Meantime (GMT) value. Depending on how time values are created, their value may or may not account for the local machine's default time zone. Mixing timestamps from different time zones (for example, in WHERE clause comparisons) can result in unexpected behavior.

CREATE VIEW

CREATE VIEW — Creates a view into a table, used to optimize access to specific columns within a table.

Syntax

```
CREATE VIEW view-name ( view-column-name [...])  
  AS SELECT table-column-name [...] COUNT(*) AS alias [, aggregate [ ,... ]]  
  FROM table-name  
  GROUP BY column-name [...]
```

Description

The CREATE VIEW statement creates a view of a table with selected columns and aggregates. VoltDB implements views as materialized views. In other words, the view is stored as a special table in the database and is updated each time the corresponding database table is updated. This means there is a small, incremental performance impact for any inserts or updates to the table, but selects on the view will execute efficiently.

The following limitations are important to note when using the CREATE VIEW statement with VoltDB:

- Views are allowed on individual tables only. Joins are not supported.
- The SELECT statement must obey the following constraints:
 - There must be a GROUP BY clause in the SELECT statement.
 - The first columns listed in the GROUP BY must match the initial columns in the SELECT statement in both name and order.
 - SELECT must include a field specified as COUNT(*). Other aggregates (SUM or COUNT) are allowed following the COUNT(*)

EXPORT TABLE

EXPORT TABLE — Specifies that a table is for export only.

Syntax

```
EXPORT TABLE table-name
```

Description

At runtime, any records written to an export-only table are queued to the export connector, as described in Chapter 13, *Exporting Live Data*. If export is enabled, this data is then passed through the connector to the export client that manages the export process.

The EXPORT TABLE statement lets you specify which tables in the schema are export-only tables. These tables become write-only. That is, they can be used in INSERT statements, but not SELECT, UPDATE, or DELETE statements.

If export is not enabled at runtime, writing to export-only tables has no effect.

PARTITION PROCEDURE

PARTITION PROCEDURE — Specifies that a stored procedure is partitioned.

Syntax

```
PARTITION PROCEDURE procedure-name ON TABLE table-name COLUMN column-name
[PARAMETER position ]
```

Description

Partitioning a stored procedure specifies that the procedure executes within a unique partition of the database. The partition in which the procedure executes is chosen at runtime based on the table and column specified by *table-name* and *column-name* and the value of the first parameter to the procedure. For example:

```
PARTITION TABLE Employees ON COLUMN BadgeNumber;
PARTITION PROCEDURE FindEmployee ON TABLE Employees COLUMN BadgeNumber;
```

The procedure FindEmployee is partitioned on the table Employees, and table Employees is in turn partitioned on the column BadgeNumber. This means that when the stored procedure FindEmployee is invoked VoltDB determines which partition to run the stored procedure in based on the value of the first parameter to the procedure and the corresponding partitioning value for the column BadgeNumber. So to find the employee with badge number 145303 you would invoke the stored procedure as follows:

```
clientResponse response = client.callProcedure("FindEmployee", 145303);
```

By default, VoltDB uses the first parameter to the stored procedure as the partitioning value. However, if you want to use the value of a different parameter, you can use the PARAMETER clause. The PARAMETER clause specifies which procedure parameter to use as the partitioning value, with *position* specifying the parameter position, counting from zero. (In other words, position 0 is the first parameter, position 1 is the second, and so on.)

The specified table must be a partitioned table and cannot be an export-only or replicated table.

PARTITION TABLE

PARTITION TABLE — Specifies that a table is partitioned and which is the partitioning column.

Syntax

```
PARTITION TABLE table-name ON COLUMN column-name
```

Description

Partitioning a table specifies that different records are stored in different unique partitions, based on the value of the specified column. The table *table-name* and column *column-name* must be valid, declared elements in the current DDL file or VoltDB generates an error when compiling the schema.

For a table to be partitioned, the partitioning column must be declared as NOT NULL. If you do not declare a partitioning column of a table in the DDL, the table is assumed to be a replicated table.

Appendix B. Supported SQL Statements

This appendix describes the SQL syntax that VoltDB supports in stored procedures.

This is not intended as a complete description of the SQL language and how it operates. Instead, it summarizes the subset of standard SQL statements that are allowed in VoltDB and any exceptions or limitations that application developers should be aware of.

The supported SQL statements are:

- DELETE
- INSERT
- SELECT
- UPDATE

DELETE

DELETE — Deletes one or more records from the database.

Syntax

```
DELETE FROM table-name
      [WHERE [NOT] boolean-expression [ {AND | OR} [NOT] boolean-expression]...]
```

Description

The DELETE statement deletes rows from the specified table that meet the constraints of the WHERE clause. The following limitations are important to note when using the DELETE statement in VoltDB:

- The DELETE statement can operate on only one table at a time (no joins or subqueries).
- The WHERE expression supports the boolean operators: equals (=), not equals (!= or <>), greater than (>), less than (<), greater than or equal to (>=), less than or equal to (<=), IS NULL, AND, OR, and NOT. Note, however, although OR is supported syntactically, VoltDB does not optimize these operations and use of OR may impact the performance of your queries.

Examples

The following example removes rows from the EMPLOYEE table where the EMPLOYEE_ID column is equal to 145303.

```
DELETE FROM employee WHERE employee_id = 145303;
```

The following example removes rows from the BID table where the BIDDERID is 12345 and the BID-PRICE is less than 100.00.

```
DELETE FROM bid WHERE bidderid=12345 AND bidprice<100.0;
```

INSERT

INSERT — creates a new row in the database, using the specified values for the columns.

Syntax

```
INSERT INTO table-name [( column-name [...]) ] VALUES ( value-expression [...])
```

Description

The INSERT statement creates a new row in the database. If you specify the column names, the values will be assigned to the columns in the order specified. If you do not specify the column names, values will be assigned to columns based on the order specified in the schema definition.

You can specify a subset of the columns in the table by specifying the column names and their desired values. However, you must specify values for any columns that are explicitly defined in the schema as NOT NULL and do not have a default value assigned.

VoltDB supports the following arithmetic operators in expressions: addition (+), subtraction (-), multiplication (*), and division (/).

Examples

The following example inserts values into the columns (firstname, mi, lastname, and emp_id) of an EMPLOYEE table:

```
INSERT INTO employee VALUES ('Jane', 'Q', 'Public', 145303);
```

The next example performs the same operation with the same results, except this INSERT statement explicitly identifies the column names and changes the order:

```
INSERT INTO employee (emp_id, lastname, firstname, mi)
VALUES (145303, 'Public', 'Jane', 'Q');
```

The last example assigns values for the employee ID and the first and last names, but not the middle initial. This query will only succeed if the MI column is nullable or has a default value defined in the database schema.

```
INSERT INTO employee (emp_id, lastname, firstname)
VALUES (145304, "Doe", "John");
```

SELECT

SELECT — fetches the specified rows and columns from the database.

Syntax

```

Select-statement [{set-operator} Select-statement ] ...

Select-statement:
    SELECT [ TOP integer-value ]
    { * | [ ALL | DISTINCT ] { column-name | selection-expression } [AS alias] [...] }
    FROM table-reference [ join-clause ]...
    [WHERE [NOT] boolean-expression [ {AND | OR} [NOT] boolean-expression]...]
    [clause...]

table-reference:
    { table-name | view-name } [AS alias]

join-clause:
    ,table-reference
    [INNER | {LEFT | RIGHT} [OUTER]] JOIN {table-reference} [join-condition]

join-condition:
    ON conditional-expression
    USING (column-reference [...])

clause:
    ORDER BY { column-name | alias } [ ASC | DESC ] [...]
    GROUP BY { column-name | alias } [...]
    LIMIT { integer-value [OFFSET row-count] | ALL }

set-operator:
    UNION [ALL]
    INTERSECT [ALL]
    EXCEPT
  
```

Description

The SELECT statement retrieves the specified rows and columns from the database, filtered and sorted by any clauses that are included in the statement. In its simplest form, the SELECT statement retrieves the values associated with individual columns. However, the selection expression can be a function such as COUNT and SUM.

The following features and limitations are important to note when using the SELECT statement with VoltDB:

- See Appendix C, *SQL Functions* for a full list of the SQL functions the VoltDB supports.
- VoltDB supports the following operators in expressions: addition (+), subtraction (-), multiplication (*), division (/) and string concatenation (||).
- TOP *n* is a synonym for LIMIT *n*.

- The WHERE expression supports the boolean operators: equals (=), not equals (!= or <>), greater than (>), less than (<), greater than or equal to (>=), less than or equal to (<=), LIKE, IS NULL, AND, OR, and NOT. Note, however, although OR is supported syntactically, VoltDB does not optimize these operations and use of OR may impact the performance of your queries.
- The boolean expression LIKE provides text pattern matching in a VARCHAR column. The syntax of the LIKE expression is {string-expression} LIKE '{pattern}' where the pattern can contain text and wildcards, including the underscore (_) for matching a single character and the percent sign (%) for matching zero or more characters. The string comparison is case sensitive.

Where an index exists on the column being scanned and the pattern starts with a text prefix (rather than starting with a wildcard), VoltDB will attempt to use the index to maximize performance. For example, a query limiting the results to rows from the EMPLOYEE table where the primary index, the JOB_CODE column, begins with the characters "Temp" looks like this:

```
SELECT * from EMPLOYEE where JOB_CODE like 'Temp%';
```

- The boolean expression IN determines if a given value is found within a list of alternatives. For example, in the following code fragment the IN expression looks to see if a record is part of Hispaniola by evaluating whether the column COUNTRY is equal to either "Dominican Republic" or "Haiti":

```
WHERE Country IN ('Dominican Republic', 'Haiti')
```

Note that the list of alternatives must be enclosed in parentheses. The result of an IN expression is equivalent to a sequence of equality conditions separated by OR. So the preceding code fragment produces the same boolean result as:

```
WHERE Country='Dominican Republic' OR Country='Haiti'
```

The advantages are that the IN syntax provides more compact and readable code and can provide improved performance by using an index on the initial expression where available.

- When using placeholders in SQL statements involving the IN list expression, you can either do replacement of individual values within the list or replace the list as a whole. For example, consider the following statements:

```
SELECT * from EMPLOYEE where STATUS IN (?, ?, ?);  
SELECT * from EMPLOYEE where STATUS IN ?;
```

In the first statement, there are three parameters that replace individual values in the IN list, allowing you to specify exactly three selection values. In the second statement the placeholder replaces the entire list, including the parentheses. In this case the parameter to the procedure call must be an array and allows you to change not only the values of the alternatives but the number of criteria considered.

The following Java code fragment demonstrates how these two queries can be used in a stored procedure, resulting in equivalent SQL statements being executed:

```
String arg1 = "Salary";  
String arg2 = "Hourly";  
String arg3 = "Parttime";  
voltQueuesQL( query1, arg1, arg2, arg3);
```

```
String listargs[] = new String[3];  
listargs[0] = arg1;  
listargs[1] = arg2;  
listargs[2] = arg3;
```

```
voltQueuesSQL( query2, (Object) listargs);
```

Note that when passing arrays as parameters in Java, it is a good practice to explicitly cast them as an object to avoid the array being implicitly expanded into individual call parameters.

- VoltDB supports both inner and outer joins. Currently, outer joins are limited to joining two tables only.
- You cannot join a table to itself.
- You can only join two or more partitioned tables if those tables are partitioned on the same value and joined on equality of the partitioning column. Joining two partitioned tables on non-partitioned columns or on a range of values is not supported. However, there are no limitations on joining to replicated tables.
- Extremely large result sets (greater than 50 megabytes in size) are not supported. If you execute a `SELECT` statement that generates a result set of more than 50 megabytes, VoltDB will return an error.

Set Operations

VoltDB also supports the set operations `UNION`, `INTERSECT`, and `EXCEPT`. These keywords let you perform set operations on two or more `SELECT` statements. `UNION` includes the combined results sets from the two `SELECT` statements, `INTERSECT` includes only those rows that appear in both `SELECT` statement result sets, and `EXCEPT` includes only those rows that appear in one result set but not the other.

Normally, `UNION` and `INTERSECT` provide a set including unique rows. That is, if a row appears in both `SELECT` results, it only appears once in the combined result set. However, if you include the `ALL` modifier, all matching rows are included. For example, `UNION ALL` will result in single entries for the rows that appear in only one of the `SELECT` results, but two copies of any rows that appear in both.

The `UNION`, `INTERSECT`, and `EXCEPT` operations obey the same rules that apply to joins:

- You cannot perform set operations on `SELECT` statements that reference the same table.
- All tables in the `SELECT` statements must either be replicated tables or partitioned tables partitioned on the same column value, using equality of the partitioning column in the `WHERE` clause.

Examples

The following example retrieves all of the columns from the `EMPLOYEE` table where the last name is "Smith":

```
SELECT * FROM employee WHERE lastname = 'Smith';
```

The following example retrieves selected columns for two tables at once, joined by the `employee_id` using an implicit inner join and sorted by last name:

```
SELECT lastname, firstname, salary  
FROM employee AS e, compensation AS c  
WHERE e.employee_id = c.employee_id  
ORDER BY lastname DESC;
```

The following example includes both a simple SQL query defined in the schema and a client application to call the procedure repeatedly. This combination uses the `LIMIT` and `OFFSET` clauses to "page" through a large table, 500 rows at a time.

When retrieving very large volumes of data, it is a good idea to use `LIMIT` and `OFFSET` to constrain the amount of data in each transaction. However, to perform `LIMIT OFFSET` queries effectively, the database

must include a tree index that encompasses all of the columns of the ORDER BY clause (in this example, the lastname and firstname columns).

Schema:

```
CREATE PROCEDURE EmpByLimit AS
  SELECT lastname, firstname FROM employee
  WHERE company = ?
  ORDER BY lastname ASC, firstname ASC
  LIMIT 500 OFFSET ?;
```

```
PARTITION PROCEDURE EmpByLimit ON TABLE Employee COLUMN Company;
```

Java Client Application:

```
long offset = 0;
String company = "ACME Explosives";
boolean alldone = false;
while ( ! alldone ) {
    VoltTable results[] = client.callProcedure("EmpByLimit",
                                                company,offset).getResults();
    if (results[0].getRowCount() < 1) {
        // No more records.
        alldone = true;
    } else {
        // do something with the results.
    }
    offset += 500;
}
```

UPDATE

UPDATE — updates the values within the specified columns and rows of the database.

Syntax

```
UPDATE table-name SET column-name = value-expression [, ...]  
[WHERE [NOT] boolean-expression [ {AND | OR} [NOT] boolean-expression ]...]
```

Description

The UPDATE statement changes the values of columns within the specified records. The following limitations are important to note when using the UPDATE statement with VoltDB:

- VoltDB supports the following arithmetic operators in expressions: addition (+), subtraction (-), multiplication (*), and division (/).
- The WHERE expression supports the boolean operators: equals (=), not equals (!= or <>), greater than (>), less than (<), greater than or equal to (>=), less than or equal to (<=), IS NULL, AND, OR, and NOT. Note, however, although OR is supported syntactically, VoltDB does not optimize these operations and use of OR may impact the performance of your queries.

Examples

The following example changes the ADDRESS column of the EMPLOYEE record with an employee ID of 145303:

```
UPDATE employee  
  SET address = '49 Lavender Sweep'  
  WHERE employee_id = 145303;
```

The following example increases the starting price by 25% for all ITEM records with a category ID of 7:

```
UPDATE item SET startprice = startprice * 1.25 WHERE categoryid = 7;
```

Appendix C. SQL Functions

Functions let you aggregate column values and perform other calculations and transformations on data within your SQL queries. This appendix lists the functions alphabetically, describing for each their syntax and purpose. The functions can also be grouped by the type of data they produce or operate on, as listed below.

Column Aggregation Functions

- AVG()
- COUNT()
- MAX()
- MIN()
- SUM()

Date and Time Functions

- EXTRACT()
- FROM_UNIXTIME()
- SINCE_EPOCH()
- TO_TIMESTAMP()
- TRUNCATE()

JSON Functions

- ARRAY_ELEMENT()
- ARRAY_LENGTH()
- FIELD()

Logic and Conversion Functions

- CAST()
- DECODE()

Math Function

- ABS()
- CEILING()
- EXP()
- FLOOR()
- POWER()
- SQRT()

String Functions

- CHAR_LENGTH()
- CONCAT()
- LEFT()
- OCTET_LENGTH()
- POSITION()
- REPEAT()
- RIGHT()

- SPACE()
- SUBSTRING()

ABS()

ABS() — Returns the absolute value of a numeric expression.

Syntax

`ABS(numeric-expression)`

Description

The ABS() function returns the absolute value of the specified numeric expression.

Example

The following example sorts the results of a SELECT expression by its proximity to a target value (specified by a placeholder), using the ABS() function to normalize values both above and below the intended target.

```
SELECT price, product_name FROM product_list
ORDER BY ABS(price - ?) ASC;
```

ARRAY_ELEMENT()

ARRAY_ELEMENT() — Returns the element at the specified location in a JSON array.

Syntax

```
ARRAY_ELEMENT( JSON-array, element-position )
```

Description

The ARRAY_ELEMENT() function extracts a single element from a JSON array. The array position is zero-based. In other words, the first element in the array is in position "0". The function returns the element as a string. For example, the following function invocation returns the string "two":

```
ARRAY_ELEMENT( '[ "zero", "one", "two", "three" ] ', 2 )
```

Note that the array element is always returned as a string. So in the following example, the function returns "2" as a string rather than an integer:

```
ARRAY_ELEMENT( '[ 0, 1, 2, 3 ] ', 2 )
```

Finally, the element may itself be a valid JSON-encoded object. For example, the following function returns the string "[0,1,2,3]":

```
ARRAY_ELEMENT( '[ [ 0, 1, 2, 3 ], [ "zero", "one", "two", "three" ] ] ', 0 )
```

The ARRAY_ELEMENT() function can be combined with other functions, such as FIELD(), to traverse more complex JSON structures. The function returns a NULL value if any of the following conditions are true:

- The position argument is less than zero
- The position argument is greater than or equal to the length of the array
- The JSON string does not represent an array (that is, the string is a valid JSON scalar value or object)

The function returns an error if the first argument is not a valid JSON string.

Example

The following example uses the ARRAY_ELEMENT() function along with FIELD() to extract specific array elements from one field in a JSON-encoded VARCHAR column:

```
SELECT language,
       ARRAY_ELEMENT(FIELD(words, 'colors'), 1) AS color,
       ARRAY_ELEMENT(FIELD(words, 'numbers'), 2) AS number
FROM world_languages WHERE language = 'French';
```

Assuming the column *words* has the following structure, the query returns the strings "French", "vert", and "trois".

```
{ "colors": [ "rouge", "vert", "bleu" ],
  "numbers": [ "un", "deux", "trois" ] }
```


ARRAY_LENGTH()

ARRAY_LENGTH() — returns the number of elements in a JSON array.

Syntax

```
ARRAY_LENGTH( JSON-array )
```

Description

The ARRAY_LENGTH() returns the length of a JSON array; that is, the number of elements the array contains. The length is returned as an integer.

The ARRAY_LENGTH() function can be combined with other functions, such as FIELD(), to traverse more complex JSON structures.

The function returns NULL if the argument is a valid JSON string but does not represent an array. The function returns an error if the argument is not a valid JSON string.

Example

The following example uses the ARRAY_LENGTH(), ARRAY_ELEMENT(), and FIELD() functions to return the last element of an array in a larger JSON string. The functions perform the following actions:

- Innermost, the FIELD() function extracts the JSON field "alerts", which is assumed to be an array, from the column *messages*.
- ARRAY_LENGTH() determines the number of elements in the array.
- ARRAY_ELEMENT() returns the last element based on the value of ARRAY_LENGTH() minus one (because the array positions are zero-based).

```
SELECT ARRAY_ELEMENT(FIELD(messages, 'alerts'),  
    ARRAY_LENGTH(FIELD(messages, 'alerts'))-1) AS last_alert,  
    station FROM reportlog  
WHERE station=?;
```

AVG()

AVG() — Returns the average of a range of numeric column values.

Syntax

`AVG(column-expression)`

Description

The AVG() function returns the average of a range of numeric column values. The values being averaged depend on the constraints defined by the WHERE and GROUP BY clauses.

Example

The following example returns the average price for each product category.

```
SELECT AVG(price), category FROM product_list
      GROUP BY category ORDER BY category;
```

CAST()

CAST() — explicitly converts an expression to the specified datatype.

Syntax

`CAST(expression AS datatype)`

Description

The CAST() function converts an expression to a specified datatype. Cases where casting is beneficial include when converting between numeric types (such as integer and float) or when converting a numeric value to a string and vice versa.

All datatypes can be used as the source or the target, except VARBINARY. You cannot use VARBINARY datatypes in expressions.

When converting from decimal values to integers, values are truncated. Where the runtime value cannot be converted, an error is thrown. Possible error conditions include:

- Converting strings to a numeric datatype and the string value is not a valid numeric representation
- Converting to a numeric datatype and the numeric value is beyond the allowable range of the target datatype
- Converting strings to TIMESTAMP and the string value is not a valid date and/or time representation

The result of the CAST() function of a null value is the corresponding null in the target datatype.

Example

The following example uses the CAST() function twice. Once with the SUBSTRING function to extract and convert the end of the product ID string to an integer value. Later to convert the results of the FIELD function so it can be used in a comparison. Note that the FIELD function always returns a string value, even for numeric data. So CAST is useful when using FIELD output in comparisons.

```
SELECT product_name,  
       SUBSTRING(prod_id FROM 1 TO 3) AS prod_category,  
       CAST(SUBSTRING(prod_id,4) AS INTEGER) AS prod_seq_num,  
FROM product_list  
WHERE CAST(FIELD(JSONdata, 'price') AS DECIMAL) < 5.99  
ORDER BY product_name;
```

CEILING()

CEILING() — Returns the smallest integer value greater than or equal to a numeric expression.

Syntax

`CEILING(numeric-expression)`

Description

The CEILING() function returns the next integer greater than or equal to the specified numeric expression. In other words, the CEILING() function "rounds up" numeric values. For example:

```
CEILING(3.1415) = 4
CEILING(2.0) = 2
CEILING(-5.32) = -5
```

Example

The following example uses the CEILING function to calculate the shipping costs for a product based on its weight in the next whole number of pounds.

```
SELECT shipping.cost_per_lb * CEILING(product.weight),
       product.prod_id FROM product, shipping
ORDER BY product.prod_id;
```

CHAR_LENGTH()

CHAR_LENGTH() — Returns the number of characters in a string.

Syntax

`CHAR_LENGTH(string-expression)`

Description

The CHAR_LENGTH() function returns the number of text characters in a string.

Note that the number of characters and the amount of physical space required to store those characters can differ. To measure the length of the string, in bytes, use the OCTET_LENGTH() function.

Example

The following example returns the string in the column LastName as well as the number of characters and length in bytes of that string.

```
SELECT LastName, CHAR_LENGTH(LastName), OCTET_LENGTH(LastName)
   FROM Customers ORDER BY LastName, FirstName;
```

CONCAT()

CONCAT() — Concatenates two strings and returns the result.

Syntax

`CONCAT(string-expression, string-expression)`

Description

The CONCAT() function concatenates two strings and returns the resulting string. The string concatenation operator || performs the same function as CONCAT().

Example

The following example concatenates the contents of two columns as part of a SELECT expression.

```
SELECT price, CONCAT(category,part_name) AS full_part_name
FROM product_list ORDER BY price;
```

The next example does something similar but uses the || operator as a shorthand to concatenate three strings, two columns and a string constant, as part of a SELECT expression.

```
SELECT lastname || ', ' || firstname AS full_name
FROM customers ORDER BY lastname, firstname;
```

COUNT()

COUNT() — Returns the number of rows selected containing the specified column.

Syntax

COUNT(*column-expression*)

Description

The COUNT() function returns the number of rows selected for the specified column. Since the actual value of the column is not used to calculate the count, you can use the asterisk (*) as a wildcard for any column. For example the query `SELECT COUNT(*) FROM widgets` returns the number of rows in the table `widgets`, without needing to know what columns the table contains.

The one case where the column name is significant is if you use the `DISTINCT` clause to constrain the selection expression. For example, `SELECT COUNT(DISTINCT last_name) FROM customer` returns the count of unique last names in the customer table.

Example

The following example returns the number of rows where the product name starts with the capital letter A.

```
SELECT COUNT(*) FROM product_list
WHERE product_name LIKE 'A%';
```

The next example returns the total number of unique product categories in the product list.

```
SELECT COUNT(DISTINCT category) FROM product_list;
```

DECODE()

DECODE() — Evaluates an expression against one or more alternatives and returns the matching response.

Syntax

```
DECODE( expression, { comparison-value, result } [...], [default-result] )
```

Description

The DECODE() function compares an expression against one or more possible comparison values. If the *expression* matches the *comparison-value*, the associated *result* is returned. If the expression does not match any of the comparison values, the *default-result* is returned. If the expression does not match any comparison value and no default result is specified, the function returns NULL.

The DECODE() function operates the same way an IF-THEN-ELSE, or CASE statement does in other languages.

Example

The following example uses the DECODE() function to interpret a coded data column and replace it with the appropriate meaning for each code.

```
SELECT title, industry, DECODE(salary_range,
    'A', 'under $25,000',
    'B', '$25,000 - $34,999',
    'C', '$35,000 - $49,999',
    'D', '$50,000 - $74,999',
    'E', '$75,000 - $99,000',
    'F', '$100,000 and over',
    'unspecified') from survey_results
order by industry, title;
```

The next example tests a value against three columns and returns the name of the column when a match is found, or a message indicating no match if none is found.

```
SELECT product_name, DECODE(?,product_name, 'PRODUCT NAME',
    part_name, 'PART NAME',
    category, 'CATEGORY',
    'NO MATCH FOUND')
FROM product_list ORDER BY product_name;
```


EXP()

EXP() — Returns the exponential of the specified numeric expression.

Syntax

`EXP(numeric-expression)`

Description

The EXP() function returns the exponential of the specified numeric expression. In other words, EXP(x) is the equivalent of the mathematical expression e^x .

Example

The following example uses the EXP function to calculate the potential population of certain species of animal projecting out ten years.

```
SELECT species, population AS current,  
       (population/2) * EXP(10*(gestation/365)*litter) AS future  
FROM animals  
WHERE species = "rabbit"  
ORDER BY population;
```

EXTRACT()

EXTRACT() — Returns the value of a selected portion of a timestamp.

Syntax

```
EXTRACT( selection-keyword FROM timestamp-expression )
```

```
EXTRACT( selection-keyword, timestamp-expression )
```

Description

The EXTRACT() function returns the value of the selected portion of a timestamp. Table C.1, “Selectable Values for the EXTRACT Function” lists the supported keywords, the datatype of the value returned by the function, and a description of its contents.

Table C.1. Selectable Values for the EXTRACT Function

Keyword	Datatype	Description
YEAR	INTEGER	The year as a numeric value.
QUARTER	TINYINT	The quarter of the year as a single numeric value between 1 and 4.
MONTH	TINYINT	The month of the year as a numeric value between 1 and 12.
DAY	TINYINT	The day of the month as a numeric value between 1 and 31.
DAY_OF_WEEK	TINYINT	The day of the week as a numeric value between 1 and 7, starting with Sunday.
DAY_OF_YEAR	SMALLINT	The day of the year as a numeric value between 1 and 366.
HOURL	TINYINT	The hour of the day as a numeric value between 0 and 23.
MINUTE	TINYINT	The minute of the hour as a numeric value between 0 and 59.
SECOND	DECIMAL	The whole and fractional part of the number of seconds within the minute as a floating point value between 0 and 60.

The timestamp expression is interpreted as a VoltDB timestamp; That is, time measured in microseconds.

Example

The following example lists all the contacts by name and birthday, listing the birthday as three separate fields for month, day, and year.

```
SELECT Last_name, first_name, EXTRACT(MONTH FROM dateofbirth),
```

```
EXTRACT(DAY FROM dateofbirth), EXTRACT(YEAR FROM dateofbirth)
FROM contact_list
ORDER BY last_name, first_name;
```

FIELD()

FIELD() — Extracts a field value from a JSON-encoded string column.

Syntax

```
FIELD( column, field-name )
```

Description

The FIELD() function extracts a field value from a JSON-encoded string. For example, assume the VARCHAR column Profile contains the following JSON string:

```
{ "first": "Charles", "last": "Dickens", "birth": 1812,
  "description": { "genre": "fiction",
                  "period": "Victorian",
                  "output": "prolific" }
}
```

It is possible to extract individual field values using the FIELD() function, as in the following SELECT statement:

```
SELECT FIELD(profile, 'first') AS firstname,
       FIELD(profile, 'last') AS lastname FROM Authors;
```

It is also possible to find records based on individual JSON fields by using the FIELD() function in the WHERE clause. For example, the following query retrieves all records from the Authors table where the JSON field birth is 1812. Note that the FIELD() function always returns a string, even if the JSON type is numeric. The comparison must match the string datatype, so the constant '1812' is in quotation marks:

```
SELECT * FROM Authors WHERE FIELD(profile, 'birth') = '1812';
```

The FIELD() function only retrieves first-level fields in the JSON object. However, it is possible to delve deeper into the JSON structure by nesting instances of the FIELD function, like so:

```
SELECT * FROM Authors WHERE
       FIELD( FIELD(profile, 'description'), 'period') = 'Victorian';
```

Two important points to note concerning input to the FIELD() function:

- If the requested field name does not exist, the function returns a null value.
- The first argument to the FIELD() function *must* be a valid JSON-encoded string. However, the content is not evaluated until the function is invoked at runtime. Therefore, it is the responsibility of the database application to ensure the validity of the content. If the FIELD() function encounters invalid content, the query will fail.

Example

The following example uses the FIELD() function to both return specific JSON fields within a VARCHAR column and filter the results based on the value of a third JSON field:

```
SELECT product_name, sku,
```

```
        FIELD(specification,'color') AS color,  
        FIELD(specification,'weight') AS weight FROM Inventory  
WHERE FIELD(specification, 'category') = 'housewares'  
ORDER BY product_name, sku;
```

FLOOR()

FLOOR() — Returns the largest integer value less than or equal to a numeric expression.

Syntax

`FLOOR(numeric-expression)`

Description

The FLOOR() function returns the largest integer less than or equal to the specified numeric expression. In other words, the FLOOR() function truncates fractional numeric values. For example:

```
FLOOR(3.1415) = 3
FLOOR(2.0) = 2
FLOOR(-5.32) = -6
```

Example

The following example uses the FLOOR function to calculate the whole number of stocks owned by a specific shareholder.

```
SELECT customer, company,
       FLOOR(num_of_stocks) AS stocks_available_for_sale
FROM shareholders WHERE customer_id = ?
ORDER BY company;
```

FROM_UNIXTIME()

FROM_UNIXTIME() — Converts a UNIX time value to a VoltDB timestamp.

Syntax

```
FROM_UNIXTIME( integer-expression )
```

Description

The FROM_UNIXTIME() function converts an integer expression to a VoltDB timestamp, interpreting the integer value as a POSIX time value; that is the number of seconds since the epoch (00:00.00 on January 1, 1970 Consolidated Universal Time). This function is a synonym for TO_TIMESTAMP(second, *integer-expression*).

Example

The following example inserts a record using FROM_UNIXTIME to convert the first argument, a POSIX time value, into a VoltDB timestamp:

```
INSERT event (when, what, where) VALUES (FROM_UNIX_TIME(?), ?, ?);
```

LEFT()

LEFT() — Returns a substring from the beginning of a string.

Syntax

LEFT(*string-expression*, *numeric-expression*)

Description

The LEFT() function returns the first n characters from a string expression, where n is the second argument to the function.

Example

The following example uses the LEFT function to return an abbreviation (the first three characters) of the product category as part of the SELECT expression.

```
SELECT LEFT(category,3), product_name, price FROM product_list
ORDER BY category, product_name;
```


MAX()

MAX() — Returns the maximum value from a range of column values.

Syntax

`MAX(column-expression)`

Description

The MAX() function returns the highest value from a range of column values. The range of values depends on the constraints defined by the WHERE and GROUP BY clauses.

Example

The following example returns the highest price in the product list.

```
SELECT MAX(price) FROM product_list;
```

The next example returns the highest price for each product category.

```
SELECT category, MAX(price) FROM product_list  
  GROUP BY category  
  ORDER BY category;
```

MIN()

MIN() — Returns the minimum value from a range of column values.

Syntax

`MIN(column-expression)`

Description

The MIN() function returns the lowest value from a range of column values. The range of values depends on the constraints defined by the WHERE and GROUP BY clauses.

Example

The following example returns the lowest price in the product list.

```
SELECT MIN(price) FROM product_list;
```

The next example returns the lowest price for each product category.

```
SELECT category, MIN(price) FROM product_list  
  GROUP BY category  
  ORDER BY category;
```

OCTET_LENGTH()

OCTET_LENGTH() — Returns the number of bytes in a string.

Syntax

`OCTET_LENGTH(string-expression)`

Description

The OCTET_LENGTH() function returns the number of bytes of data in a string.

Note that the number of bytes required to store a string and the actual characters that make up the string can differ. To count the number of characters in the string use the CHAR_LENGTH() function.

Example

The following example returns the string in the column LastName as well as the number of characters and length in bytes of that string.

```
SELECT LastName, CHAR_LENGTH(LastName), OCTET_LENGTH(LastName)
   FROM Customers ORDER BY LastName, FirstName;
```

POSITION()

POSITION() — Returns the starting position of a substring in another string.

Syntax

POSITION(*substring-expression* IN *string-expression*)

Description

The POSITION() function returns the starting position of a substring in another string. The position, if a match is found, is an integer number between one and the length of the string being searched. If no match is found, the function returns zero.

Example

The following example selects all books where the title contains the word "poodle" and returns the book's title and the position of the substring "poodle" in the title.

```
SELECT Title, POSITION('poodle' IN Title) FROM Books
WHERE Title LIKE '%poodle%' ORDER BY Title;
```

POWER()

POWER() — Returns the value of the first argument raised to the power of the second argument.

Syntax

`POWER(numeric-expression, numeric-expression)`

Description

The POWER() function takes two numeric expressions and returns the value of the first raised to the power of the second. In other words, POWER(x,y) is the equivalent of the mathematical expression x^y .

Example

The following example uses the POWER function to return the surface area and volume of a cube.

```
SELECT length, 6 * POWER(length,2) AS surface,  
       POWER(length,3) AS volume FROM Cube  
ORDER BY length;
```

REPEAT()

REPEAT() — Returns a string composed of a substring repeated the specified number of times.

Syntax

```
REPEAT( string-expression, numeric-expression )
```

Description

The REPEAT() function returns a string composed of the substring *string-expression* repeated *n* times where *n* is defined by the second argument to the function.

Example

The following example uses the REPEAT and the CHAR_LENGTH functions to replace a column's actual contents with a mask composed of the letter "X" the same length as the original column value.

```
SELECT username, REPEAT('X', CHAR_LENGTH(password)) as Password
FROM accounts ORDER BY username;
```

RIGHT()

RIGHT() — Returns a substring from the end of a string.

Syntax

RIGHT(*string-expression*, *numeric-expression*)

Description

The RIGHT() function returns the last *n* characters from a string expression, where *n* is the second argument to the function.

Example

The following example uses the LEFT() and RIGHT() functions to return an abbreviated summary of the Description column, ensuring the result fits within 20 characters.

```
SELECT product_name,  
       LEFT(description,10) || '...' || RIGHT(description,7)  
FROM product_list ORDER BY product_name;
```

SINCE_EPOCH()

SINCE_EPOCH() — Converts a VoltDB timestamp to an integer number of time units since the POSIX epoch.

Syntax

```
SINCE_EPOCH( time-unit, timestamp-expression )
```

Description

The **SINCE_EPOCH()** function converts a VoltDB timestamp into an 64-bit integer value (BIGINT) representing the equivalent number since the POSIX epoch in a specified time unit. POSIX time is usually represented as the number of seconds since the epoch; that is, since 00:00.00 on January 1, 1970 Consolidated Universal Time (UTC). So the function **SINCE_EPOCH(SECONDS, timestamp)** returns the POSIX time equivalent for the value of timestamp. However, you can also request the number of milliseconds or microseconds since the epoch. The valid keywords for specifying the time units are:

- **SECOND** — Seconds since the epoch
- **MILLISECOND**, **MILLIS** — Milliseconds since the epoch
- **MICROSECOND**, **MICROS** — Microseconds since the epoch

You cannot perform arithmetic on timestamps directly. So **SINCE_EPOCH()** is useful for performing calculations on timestamp values in SQL expressions. For example, the following SQL statement looks for events that are less than a minute in length, based on the timestamp columns **STARTTIME** and **ENDTIME**:

```
SELECT * FROM Event
  WHERE ( SINCE_EPOCH(Second, endtime)
        - SINCE_EPOCH(Second, starttime) ) < 60;
```

The **TO_TIMESTAMP()** function performs the inverse of **SINCE_EPOCH()**, by converting an integer value to a VoltDB timestamp based on the specified time units.

Example

The following example returns a timestamp column as the equivalent POSIX time value.

```
SELECT event_id, event_name,
       SINCE_EPOCH(Second, starttime) as posix_time FROM Event
ORDER BY event_id;
```

The next example uses **SINCE_EPOCH()** to return the length of an event, in microseconds, by calculating the difference between two timestamp columns.

```
SELECT event_type,
       SINCE_EPOCH(Microsecond, endtime)
       -SINCE_EPOCH(Microsecond, starttime) AS delta
FROM Event GROUP BY event_type;
```


SPACE()

SPACE() — Returns a string of spaces of the specified length.

Syntax

SPACE(*numeric-expression*)

Description

The SPACE() function returns a string composed of n spaces where the string length n is specified by the function's argument. SPACE(n) is a synonym for REPEAT(' ', n).

Example

The following example uses the SPACE and CHAR_LENGTH functions to ensure the result is a fixed length, padded with blank spaces.

```
SELECT product_name || SPACE(80 - CHAR_LENGTH(product_name))  
FROM product_list ORDER BY product_name;
```

SQRT()

SQRT() — Returns the square root of a numeric expression.

Syntax

`SQRT(numeric-expression)`

Description

The SQRT() function returns the square root of the specified numeric expression.

Example

The following example uses the SQRT and POWER functions to return the distance of a graph point from the origin.

```
SELECT location, x, y,  
       SQRT(POWER(x,2) + POWER(y,2)) AS distance  
FROM points ORDER BY location;
```

SUBSTRING()

SUBSTRING() — Returns the specified portion of a string expression.

Syntax

```
SUBSTRING( string-expression FROM position [TO length] )
```

```
SUBSTRING( string-expression, position [, length] )
```

Description

The SUBSTRING() function returns a specified portion of the string expression, where *position* specifies the starting position of the substring (starting at position 1) and *length* specifies the maximum length of the substring. The length of the returned substring is the lower of the remaining characters in the string expression or the value specified by *length*.

For example, if the string expression is "ABCDEF" and position is specified as 3, the substring starts with the character "C". If length is also specified as 3, the return value is "CDE". If, however, the length is specified as 5, only the remaining four characters "CDEF" are returned.

If *length* is not specified, the remainder of the string, starting from the specified by *position*, is returned. For example, SUBSTRING("ABCDEF",3) and SUBSTRING("ABCDEF"3,4) return the same value.

Example

The following example uses the SUBSTRING function to return the month of the year, which is a VARCHAR column, as a three letter abbreviation.

```
SELECT event, SUBSTRING(month,1,3), day, year FROM calendar  
ORDER BY event ASC;
```

SUM()

SUM() — Returns the sum of a range of numeric column values.

Syntax

SUM(*column-expression*)

Description

The SUM() function returns the sum of a range of numeric column values. The values being added together depend on the constraints defined by the WHERE and GROUP BY clauses.

Example

The following example uses the SUM() function to determine how much inventory exists for each product type in the catalog.

```
SELECT category, SUM(quantity) AS inventory FROM product_list
      GROUP BY category ORDER BY category;
```

TO_TIMESTAMP()

TO_TIMESTAMP() — Converts an integer value to a VoltDB timestamp based on the time unit specified.

Syntax

`TO_TIMESTAMP(time-unit, integer-expression)`

Description

The TO_TIMESTAMP() function converts an integer expression to a VoltDB timestamp, interpreting the integer value as the number of specified time units since the POSIX epoch. POSIX time is usually represented as the number of seconds since the epoch; that is, since 00:00.00 on January 1, 1970 Consolidated Universal Time (UTC). So the function TO_TIMESTAMP(Second, timeinsecs) returns the VoltDB TIMESTAMP equivalent of timeinsecs as a POSIX time value. However, you can also request the integer value be interpreted as milliseconds or microseconds since the epoch. The valid keywords for specifying the time units are:

- SECOND — Seconds since the epoch
- MILLISECOND, MILLIS — Milliseconds since the epoch
- MICROSECOND, MICROS — Microseconds since the epoch

You cannot perform arithmetic on timestamps directly. So TO_TIMESTAMP() is useful for converting the results of arithmetic expressions to VoltDB TIMESTAMP values. For example, the following SQL statement uses TO_TIMESTAMP to convert a POSIX time value before inserting it into a VoltDB TIMESTAMP column:

```
INSERT Event (event_id,event_name,event_type, starttime)
VALUES(?,?,?,TO_TIMESTAMP(Second, ?));
```

The SINCE_EPOCH() function performs the inverse of TO_TIMESTAMP(), by converting a VoltDB TIMESTAMP to an integer value based on the specified time units.

Example

The following example updates a TIMESTAMP column, adding one hour (in seconds) to the current value using SINCE_EPOCH() and TO_TIMESTAMP() to perform the conversion and arithmetic:

```
UPDATE Contest
SET deadline=TO_TIMESTAMP(Second, SINCE_EPOCH(Second,deadline) + 3600)
WHERE expired=1;
```

TRUNCATE()

TRUNCATE() — truncates a VoltDB timestamp to the specified time unit.

Syntax

`TRUNCATE(time-unit, timestamp)`

Description

The TRUNCATE() function truncates a timestamp value to the specified time unit. For example, if the timestamp column Apollo has the value July 20, 1969 4:17:40 P.M, then using the function TRUNCATE(hour,apollo) would return the value July 20, 1969 4:00:00 P.M. Allowable time units for truncation include the following:

- YEAR
- QUARTER
- MONTH
- DAY
- HOUR
- MINUTE
- SECOND
- MILLISECOND, MILLIS

Example

The following example uses the TRUNCATE function to find records where the timestamp column, incident, falls within a specific day, entered as a POSIX time value.

```
SELECT incident, description FROM securitylog
WHERE TRUNCATE(DAY, incident) = TRUNCATE(DAY, FROM_UNIXTIME(?))
ORDER BY incident, description;
```

Appendix D. VoltDB CLI Commands

VoltDB provides shell or CLI (command line interpreter) commands to perform common functions for developing, starting, and managing VoltDB applications and databases. This appendix describes those shell commands in detail.

The commands are listed in alphabetical order.

- csvloader
- dragent
- exporttofile
- sqlcmd
- voltadmin
- voltdb

csvloader

csvloader — Imports the contents of a CSV file and inserts it into a VoltDB table.

Syntax

```
csvloader table-name [arguments]
csvloader -p procedure-name [arguments]
```

Description

The csvloader command reads comma-separated values and inserts each valid line of data into the specified table in a VoltDB database. The most common way to use csvloader is to specify the database table to be loaded and a CSV file containing the data, like so:

```
$ csvloader employees -f acme_employees.csv
```

Alternately, you can use standard input as the source of the data:

```
$ csvloader employees < acme_employees.csv
```

In addition to inserting all valid content into the specified database table, csvloader creates three output files:

- **Error log** — The error log provides details concerning any errors that occur while processing the input file. This includes errors in the format of the input as well as errors that occur attempting the insert into VoltDB. For example, if two rows contain the same value for a column that is declared as unique, the error log indicates that the second insert fails due to a constraint violation.
- **Failed input** — A separate file contains the contents of each line that failed to load. This file is useful because it allows you to correct any formatting issues and retry just the failed content, rather than having to restart and reload the entire table.
- **Summary report** — Once all input lines are processed, csvloader generates a summary report listing how many lines were read, how many were successfully loaded and how long the operation took.

All three files are created, by default, in the current working directory using "csvloader" and the table name as prefixes. For example, using csvloader to insert contestants into the sample voter database creates the following files:

```
csvloader_contestants_insert_log.log
csvloader_contestants_invalidrows.csv
csvloader_contestants_insert_report.log
```

Arguments

--blank {error | null | empty }

Specifies what to do with missing values in the input. By default, if a line contains a missing value, an error is reported and the input line ignored. If you do not want missing values to be interpreted as an error, you can use the --blank argument to specify other behaviors. Specifying --blank null enters a null, in the appropriate datatype, as the column value. Specifying --blank empty returns the corresponding "empty" value in the appropriate datatype. An empty value is interpreted as the following:

- Zero for all numeric columns
- Zero, or the Unix epoch value, for timestamp columns
- An empty or zero-length string for VARCHAR and VARBINARY columns

--columnsize limit *{integer}*

Specifies the maximum size of quoted column input, in bytes. Mismatched quotation marks in the input can cause csvloader to read all subsequent input — including line breaks — as part of the column. To avoid excessive memory use in this situation, the flag sets a limit on the maximum number of bytes that will be accepted as input for a column that is enclosed in quotation marks and spans multiple lines. The default is 16777216 (that is, 16MB).

--escape *{character}*

Specifies the escape character that must precede a separator or quotation character that is supposed to be interpreted as a literal character in the CSV input. The default escape character is the backslash (\).

-f, --file *{file-specification}*

Specifies the location of a CSV file to read as input. If you do not specify an input file, csvloader reads input from standard input.

--limit rows *{integer}*

Specifies the maximum number of rows to be read from the input stream. This argument (along with --skip) lets you load a subset of a larger CSV file.

-m, --max errors *{integer}*

Specifies the target number of errors before csvloader stops processing input. Once csvloader encounters the specified number of errors while trying to insert rows, it will stop reading input and end the process. Note that, since csvloader performs inserts asynchronously, it often attempts more inserts before the target number of exceptions are returned from the database. So it is possible more errors could be returned after the target is met. This argument lets you conditionally stop a large loading process if more than an acceptable number of errors occur.

--no whitespace

Specifies that the CSV input must not contain any whitespace between data values and separators. By default, csvloader ignores extra space between values, quotation marks, and the value separators. If you use this argument, any input lines containing whitespace will generate an error and not be inserted into the database.

--password *{text}*

Specifies the password to use when connecting to the database. You must specify a username and password if security is enabled for the database.

--port *{port-number}*

Specifies the network port to use when connecting to the database. If you do not specify a port, csvloader uses the default client port 21212.

-p, --procedure *{procedure-name}*

Specifies a stored procedure to use for loading each record from the data file. The named procedure must exist in the database catalog and must accept the fields of the data record as input parameters. By default, csvloader uses the default insert procedure `{TABLE-NAME}.insert`.

--quote char *{character}*

Specifies the quotation character that is used to enclose values. By default, the quotation character is the double quotation mark (").

`-r, --reportdir {directory}`

Specifies the directory where csvloader writes the three output files. By default, csvloader writes output files to the current working directory. This argument lets you redirect output to an alternative location.

`--s, --servers=server-id[,...]`

Specifies the network address of one or more nodes of a database cluster. By default, csvloader attempts to insert the CSV data into a database on the local system (localhost). To load data into a remote database, use the `--servers` argument to specify the database nodes the loader should connect to.

`--separator {character}`

Specifies the character used to separate individual values in the input. By default, the separator character is the comma (,).

`--skip {integer}`

Specifies the number of lines from the input stream to skip before inserting rows into the database. This argument (along with `--limitrows`) lets you load a subset of a larger CSV file.

`--strictquotes`

Specifies that all values in the CSV input must be enclosed in quotation marks. If you use this argument, any input lines containing unquoted values will generate an error and not be inserted into the database.

`--user {text}`

Specifies the username to use when connecting to the database. You must specify a username and password if security is enabled for the database.

Examples

The following example loads the data from a CSV file, `languages.csv`, into the `helloworld` table from the Hello World example database and redirects the output files to the `./logs` subfolder.

```
$ csvloader helloworld -f languages.csv -r ./logs
```

The following example performs the same function, providing the input interactively.

```
$ csvloader helloworld -r ./logs
"Hello", "World", "English"
"Bonjour", "Monde", "French"
"Hola", "Mundo", "Spanish"
"Hej", "Verden", "Danish"
"Ciao", "Mondo", "Italian"
CTRL-D
```

dragent

dragent — Starts the database replication agent.

Syntax

```
dragent master server-id[:port-num] replica server-id[:port-num] [statsinterval seconds] [user-  
name username-string password password-string]
```

Description

The dragent command starts the database replication agent and begins replicating the master database to the replica. See Chapter 12, *Database Replication* for more information about the database replication process.

Arguments

master *server-id[:port-num]*

Specifies the network address of one node from the master database cluster. The server-id can be an IP address or hostname. The port number to connect to is optional. By default, the replication agent uses the standard client port.

replica *server-id[:port-num]*

Specifies the network address of one node from the replica database cluster. The server-id can be an IP address or hostname. The port number to connect to is optional. By default, the replication agent uses the standard client port.

If security is enabled for the replica database, you must also specify a username and password as additional arguments. For example, the following command connects to the replica database *antarctic* using the username *penguin* and password *wheretheylive*:

```
$ dragent master arctic replica antarctic \  
    username penguin password wheretheylive
```

statsinterval *seconds*

Specifies the frequency with which the agent reports statistics concerning the replication throughput. These statistics are useful in determining if replication is keeping up with the throughput from the master database.

Example

The following example starts database replication between the master database cluster that includes the node zeus and the replica database cluster that includes the node apollo. The replication agent uses the admin port to connect to apollo.

```
$ dragent master zeus replica apollo:21211
```

exporttofile

exporttofile — Starts the export client, connects to a database, and writes export data to one or more files.

Syntax

```
exporttofile --servers {host-name[:port]} --nonce {unique-id} --connect {client | admin} --type {csv | tsv} [optional-arguments...]
exporttofile help
```

Description

The exporttofile command starts the export client, connects to a running VoltDB database, fetches queued export data and writes it to one or more files on the local system. The command arguments can appear in any order. However, the `--servers`, `--nonce`, `--connect`, and `--type` arguments are all required.

The export client writes data out to disk, one file per database table, "rolling" over to new files periodically. The filenames of the exported data are constructed from:

- A unique prefix (specified with `--nonce`)
- A unique value identifying the current version of the database catalog
- The table name
- A timestamp identifying when the file was started

While the file is being written, the file name also contains the prefix "active-". Once the file is complete and a new file started, the "active-" prefix is removed. Therefore, any export files without the prefix are complete and can be copied, moved, deleted, or post-processed as desired.

See Chapter 13, *Exporting Live Data* for more information about how export works.

Arguments

`--servers {host-name[:port]} [...]`

A comma separated list of host names or IP addresses to query.

`--nonce {text}`

The prefix to use for the files that the client creates. The client creates a separate file for every table that is exported, constructing a file name that includes a transaction ID, the nonce, the name of the table, a timestamp, and a file type specified by the `--type` argument.

`--connect {client | admin}`

The port to connect to. You specify the type of port (client or admin), not the port number.

`--type {csv | tsv}`

The type of files to create. You can specify either csv (for comma-separated files) or tsv (for tab-delimited files).

`--user {text}`

The username to use for authenticating to the VoltDB server(s). Required only if security is enabled for the database.

`--password {text}`

The password to use for authenticating to the VoltDB server(s). Required only if security is enabled for the database. If you specify a username but not a password, the export client prompts you for the password.

`--outdir {path}`

(Optional.) The directory where the output files are created. If you do not specify an output path, the client writes the output files to the current default directory.

`--period {integer}`

(Optional.) The frequency, in minutes, for "rolling" the output file. The default frequency is 60 minutes.

`--batched`

(Optional.) Store the output files in subfolders that are "rolled" according to the frequency specified by `--period`. The subfolders are named according to the nonce and the timestamp, with "active-" prefixed to the subfolder currently being written.

`--with-schema`

(Optional.) Writes a JSON representation of each table's schema as part of the export. The primary output files of the export-to-file client contain the exported data in rows, but do not identify the datatype of each column. The JSON schema files can be used to ensure the appropriate datatype and precision is maintained if and when the output files are imported into another system.

`--binaryencoding {base64 | hex}`

(Optional.) The format to use when encoding VARBINARY data for output. Binary data is encoded in either BASE64 or hexadecimal format. The default is hexadecimal.

`--delimiters {text}`

(Optional.) Alternate delimiter characters for the CSV output. The text string specifies four characters: the field delimiter, the enclosing character, the escape character, and the record delimiter. To use special or non-printing characters (including the space character) encode the character as an html entity. For example "<" for the "less than" symbol.

`--dateformat {format-string}`

(Optional.) The format of the date used when constructing the output file names. You specify the date format as a Java SimpleDateFormat string. The default format is "yyyyMMddHHmmss".

`--timezone {text}`

(Optional.) The time zone to use when formatting the timestamp. Specify the time zone as a Java timezone identifier. The default is GMT.

`--skipinternals`

(Optional.) Eliminates the six columns of VoltDB metadata (such as transaction ID and timestamp) from the output. If you specify `--skipinternals` the output files contain only the exported table data.

Example

The following example connects the export client to a database cluster including the servers zeus and athena and stores the export data as csv files using the unique identifier `olympus` in a subfolder called `/greece`.

```
$ exporttofile --servers zeus,athena \
               --nonce olympus \
```

```
--connect client \  
--type csv \  
--outdir ./greece
```

sqlcmd

sqlcmd — Starts an interactive command prompt for issuing SQL queries to a running VoltDB database

Syntax

`sqlcmd [args...]`

Description

The sqlcmd command starts an interactive session and provides its own command line prompt until you exit the session. When you start the session, you can optionally specify one or more database servers to access. By default, sqlcmd assumes the database is accessible via localhost.

At the sqlcmd prompt, you have three key options:

- **SQL queries** — You can enter ad hoc SQL queries that are run against the database and the results displayed. You must terminate the query with a semi-colon and carriage return.
- **Procedure calls** — You can have sqlcmd execute a stored procedure. You identify a procedure call with the exec command, followed by the procedure class name, the procedure parameters, and a closing semi-colon. For example, the following sqlcmd command executes the @SystemCatalog system procedure requesting information about the stored procedures.

```
$ sqlcmd
1> exec @SystemCatalog procedures;
```

Note that string values are entered as plain text and are not enclosed in quotation marks. Also, the exec command must be terminated by a semi-colon.

- **Exit** — When you are done with your interactive session, enter the exit command to end the session and return to the shell prompt.

For information about additional sqlcmd commands and keyboard control while using the interactive command prompt, see the sqlcmd help text by using the `--help` argument when invoking sqlcmd. For example:

```
$ sqlcmd --help
```

Arguments

`--help`

Displays the sqlcmd help text then returns to the shell prompt.

`--servers=server-id[,...]`

Specifies the network address of one or more nodes in the database cluster. By default, sqlcmd attempts to connect to a database on localhost.

`--port=port-num`

Specifies the port number to use when connecting to the database servers. All servers must be using the same port number. By default, sqlcmd connects to the standard client port (21212).

`--user=user-id`

Specifies the username to use for authenticating to the database. The username is required if the database has security enabled.

`--password=password-string`

Specifies the password to use for authenticating to the database. The password is required if the database has security enabled.

`--output-format={csv | fixed | tab}`

Specifies the format of the output of query results. Output can be formatted as comma-separated values (csv), fixed monospaced text (fixed), or tab-separated text fields (tab). By default, the output is in fixed monospaced text.

`--output-skip-metadata`

Specifies that the column headings and other metadata associated with query results are not displayed. By default, the output includes such metadata. However, you can use this argument, along with the `--output-format` argument, to write just the data itself to an output file.

Example

The following example demonstrates an `sqlcmd` session, accessing the voter sample database running on node zeus.

```
$ sqlcmd --servers=zeus
```

```
SQL Command :: zeus:21212
```

```
1> select * from contestants;
```

```
1 Edwina Burnam
2 Tabatha Gehling
3 Kelly Clauss
4 Jessie Alloway
5 Alana Bregman
6 Jessie Eichman
```

```
(6 row(s) affected)
```

```
2> select sum(num_votes) as total, contestant_number from
v_votes_by_contestant_number_State group by contestant_number
order by total desc;
```

```
TOTAL    CONTESTANT_NUMBER
-----
757240    1
630429    6
442962    5
390353    4
384743    2
375260    3
```

```
(6 row(s) affected)
```

```
3> exit
```

```
$
```


voltadmin

voltadmin — Performs administrative functions on a VoltDB database.

Syntax

```
voltadmin [args...] {command}
```

Description

The voltadmin command allows you to perform administrative tasks on a VoltDB database. You specify the database server to access and, optionally, authentication credentials using arguments to the voltadmin command. Individual administrative commands may have they own unique arguments as well.

Arguments

The following global arguments are available for all voltadmin commands.

- h, --help
Displays information about how to use a command. The --help flag and the help command perform the same function.
- H, --host=*server-id[:port]*
Specifies which database server to connect to. You can specify the server as a network address or hostname. By default, voltadmin attempts to connect to a database on localhost. You can optionally specify the port number. If you do not specify a port, voltadmin uses the default admin port.
- p, --password=*password*
Specifies the password to use for authenticating to the database. The password is required if the database has security enabled..
- u, --user=*user-id*
Specifies the username to use for authenticating to the database. The username is required if the database has security enabled.
- v, -verbose
Displays additional information about the specific commands being executed.

Commands

The following are the administrative functions that you can invoke using voltadmin.

- help [*command*]
Displays information about the usage of individual commands or, if you do not specify a command, summarizes usage information for all commands. The **help** command and **--help** qualifier are synonymous.
- pause
Pauses the database, stopping any additional activity on the client port.
- promote
Promotes a replica database, stopping replication and enabling read/write queries on the client port.

resume

Resumes normal database operation after a pause.

save {directory} {unique-ID}

Creates a snapshot containing the current database contents. The contents are saved to disk on the server(s) using the unique ID as a file prefix and the directory specification as the file path. Additional arguments for the **save** command are:

--format={ csv | native }

Specifies the format of the snapshot files. The allowable formats are CSV (comma-separated value) and native formats. Native format snapshots can be used for restoring the database. CSV files can be used by other utilities (such as spreadsheets or the VoltDB CSV loader) but cannot be restored using the **voltadmin restore** command.

--blocking

Specifies that the snapshot will block all other transactions until the snapshot is complete. The advantage of blocking snapshots is that once the command completes you know the snapshot is finished. The disadvantage is that the snapshot blocks ongoing use of the database.

By default, voltadmin performs non-blocking snapshots so as not to interfere with ongoing database operation. However, note that the non-blocking **save** command only starts the snapshot. You must use **show snapshots** to determine when the snapshot process is finished if you want to know when it is safe, for example, to shutdown the database.

restore {directory} {unique-ID}

Restores the data from a snapshot to the database. The data is read from a snapshot using the same unique ID and directory path that were used when the snapshot was created.

show snapshots

Displays information about up to ten previous snapshots. This command is useful for determining the success or failure of snapshots started with the **save** command.

update {catalog} {deployment}

Updates the catalog and deployment configuration on a running database. There are some limitations on what changes can be made on a live update. For example, you cannot rename a table or change its partitioning column. See the description of the @UpdateApplicationCatalog stored procedure for details.

shutdown

Stops the database.

Example

The following example illustrates one way to perform an orderly shutdown of a VoltDB cluster, including pausing and saving the database contents.

```
$ voltadmin pause
$ voltadmin save --blocking ./ mydb
$ voltadmin shutdown
```

voltadb

voltadb — Performs management tasks on the current server, such as compiling the application catalog and starting the database.

Syntax

```
voltadb collect [args] voltadbroot-directory

voltadb compile [args] [DDL-file ...]

voltadb create [replica] {catalog application-catalog} [host host-id] [deployment deployment-file]
    [license license-file]

voltadb recover [host host-id] [deployment deployment-file] [license license-file]

voltadb add host host-id license license-file

voltadb [live] rejoin host host-id [deployment deployment-file] [license license-file]
```

Description

The **voltadb** command performs local management functions on the current system, including:

- Compiling schema files and stored procedures into an application catalog
- Starting the database process
- Collecting log files into a single compressed file

The action that is performed depends on which start action you specify to the **voltadb** command:

- **collect** — the **collect** option collects system and process logs related to the VoltDB database process on the current system and compresses them into a single file. This command is helpful when reporting problems to VoltDB support. The only required argument to the **collect** command is the path to the **voltadbroot** directory where the database was run. By default, the root directory is a subfolder, **voltadbroot**, in the current working directory where the database was started.
- **compile** — the **compile** option compiles the database schema and stored procedures into an application catalog. You can specify one or more data definition language (DDL) files that describe the schema of the database, the stored procedures, and the partitioning columns. See Appendix A, *Supported SQL DDL Statements* for the SQL statements supported in the DDL files. The output of the **compile** action is an application catalog that can be used to start the VoltDB database. The default output filename is **catalog.jar**. However, you can use the **--output** argument to specify a different file name or location. See the next section for other arguments to the **compile** action.
- **create** — the **create** option starts a new, empty database. This option is useful when starting a database for the first time or if you are updating the catalog by performing a save, shutdown, startup, and restore. (See Chapter 7, *Updating Your VoltDB Database* for information on updating your application catalog.)
- **recover** — the **recover** option starts the database and restores a previous state from the last known snapshot or from command logs. VoltDB uses the snapshot and command log paths specified in the deployment file when looking for content to restore. If you specify **recover** as the startup action and no snapshots or command logs can be found, startup will fail.

- **add** — the add option adds the current node to an existing cluster. To add nodes "on the fly" the cluster must be started with the elastic option enabled in the deployment file. See Section 7.4, "Updating the Hardware Configuration" for details on elastic scaling.
- **rejoin** — If a node on a K-safe cluster fails, you can use the rejoin start action to have the node (or a replacement node) rejoin the cluster. The host-id you specify with the host argument can be any node still present in the database cluster; it does *not* have to be the host node specified when the cluster was started. You can also request a live rejoin by including the **live** keyword.

Finally, when starting a new database you can include the **replica** keyword to create a recipient for database replication.

When starting the database, the voltdb command uses Java to instantiate the process. It is possible to customize the Java environment, if necessary, by passing command line arguments to Java through the following environment variables:

- **LOG4J_CONFIG_PATH** — Specifies an alternate Log4J configuration file.
- **VOLTDDB_HEAPMAX** — Specifies the maximum heap size for the Java process. Specify the value as an integer number of megabytes. By default, the maximum heap size is set to 1024.
- **VOLTDDB_OPTS** — Specifies all other Java command line arguments. You must include both the command line flag and argument. For example, this environment variable can be used to specify system properties using the -D flag:

```
export VOLTDDB_OPTS="-DmyApp.DebugFlag=true"
```

Log Collection Arguments

The following arguments apply specifically to the **collect** action.

--dry-run

Lists the actions that will be taken, including the files that will be collected, but does not actually perform the collection or upload.

--no-prompt

Specifies that the process will not prompt for input, such as whether to delete the output file after uploading is complete. This argument is useful when starting the collect action from within a script.

--prefix={file-prefix}

Specifies the prefix for the resulting output file. The default prefix is "voltdb_logs".

--skip-heap-dump

Specifies that the heap dump not be included in the collection. The heap dump is usually significantly larger than the other log files and can be excluded to save space.

--upload={host}

Specifies a host server to which the output file will be uploaded using SFTP.

--username={account-name}

Specifies the SFTP account to use when using the --upload option. If you specify --upload but not --username, you will be prompted for the account name.

--password={password}

Specifies the password to use when using the --upload option. If you specify --upload but not --password, you will be prompted for the password.

Schema Compilation Arguments

The following arguments apply specifically to the **compile** action.

-classpath={*Java-classpath*}

Specifies additional classpath locations for the compilation process to search when looking for stored procedure class files. The classpath you specify with this argument is appended to any existing classpath definition.

-o, --output={*application-catalog*}

Specifies the file and path name to use for the application catalog that is created as a result of the compilation.

-p, --project={*project-definition-file*}

(Deprecated) Specifies a project definition file to use instead of a DDL file. This argument is provided for compiling old VoltDB projects. All of the features of the project definition file used in previous versions of VoltDB are now available as DDL syntax, removing the need for a separate project file and simplifying the development process.

Database Startup Arguments

The following arguments apply to the **add**, **create**, **recover**, and **rejoin** start actions.

catalog {*application-catalog*}

Specifies the application catalog containing the schema and stored procedures to load when starting the database. Two special notes concerning the catalog:

- The catalog must be identical on all nodes when starting a cluster.
- The catalog specified on the command line is only used when creating a new database.

If you recover previous data using the **recover** start action, the catalog saved with the snapshot or command log is loaded and any catalog you specify on the command line is ignored.

host {*host-id*}

Specifies the network address of the node that coordinates the start or rejoining of the database. When starting a database, all nodes must specify the same host address. Note that once the database starts and the cluster is complete, the role of the host node is complete and all nodes become peers.

When rejoining or adding a node, you can specify any node still in the cluster as the host. The host for a rejoin operation does *not* have to be the same node as the host specified when the database started.

The default if you do not specify a host when starting the database is `localhost`. In other words, a single node cluster running on the current system. You must specify a host on the command line when rejoining a node.

deployment {*deployment-file*}

Specifies the location of the database configuration file. The configuration file is an XML file that defines the database configuration, including the initial size of the cluster and which options are enabled when the database is started. See Appendix E, *Deployment File (deployment.xml)* for a complete description of the syntax of the configuration file.

The default, if you do not specify a deployment file, is a single node cluster without K-safety and with two sites per host.

license *{license-file}*

Specifies the location of the license file, which is required when using the VoltDB Enterprise Edition. The argument is ignored when using the community edition.

Network Configuration Arguments

In addition to the arguments listed above, there are additional arguments that specify the network configuration for server ports and interfaces when starting a VoltDB database. In most cases, the default values can and should be accepted for these settings. The exceptions are the external and internal interfaces that should be specified whenever there are multiple network interfaces on a single machine.

The network configuration arguments to the **voltdb** command are listed below. See the appendix on server configuration options in the *VoltDB Management Guide* for more information about network configuration options.

externalinterface *{ip-address}*

Specifies which network interface to use for external ports, such as the admin and client ports.

internalinterface *{ip-address}*

Specifies which network interface to use for internal communication, such as the internal and zookeeper ports.

internalport *{port-number}*

Specifies the internal port number used to communicate between cluster nodes.

port *{port-number}*

Specifies the client port number.

replicationport *{port-number}*

Specifies the first of three replication ports used for database replication.

zkport *{port-number}*

Specifies the zookeeper port number.

Examples

The first example uses the compile action to create an application catalog from two DDL files. The `--classpath` argument specifies the location of the stored procedure class files.

```
$ voltdb compile --classpath=./obj employees.sql company.sql
```

The next example shows the command for creating a database running the voter sample application, using a custom configuration file, `2nodedeploy.xml`, and the node `zeus` as the host.

```
$ voltdb create catalog voter.jar deployment 2nodedeploy.xml \
    host zeus
```

The following example takes advantage of the defaults for the host and deployment arguments to start a single-node database on the current system using the voter catalog.

```
$ voltdb create catalog voter.jar
```

Appendix E. Deployment File (deployment.xml)

The deployment file describes the physical configuration of a VoltDB database cluster at runtime, including the number of hosts in the cluster and the number of sites per hosts, among other things. This appendix describes the syntax for each component within the deployment file.

The deployment file is a fully-conformant XML file. If you are unfamiliar with XML, see Section E.1, “Understanding XML Syntax” for a brief explanation of XML syntax.

E.1. Understanding XML Syntax

The deployment file is a fully-conformant XML file. XML files consist of a series of nested *elements* identified by beginning and ending “tags”. The beginning tag is the element name enclosed in angle brackets and the ending tag is the same except that the element name is preceded by a slash. For example:

```
<deployment>
  <cluster>
  </cluster>
</deployment>
```

Elements can be nested. In the preceding example `cluster` is a child of the element `deployment`.

Elements can also have *attributes* that are specified within the starting tag by the attribute name, an equals sign, and its value enclosed in single or double quotes. In the following example the `hostcount` and `sitesperhost` attributes of the `cluster` element are assigned values of “2” and “4”, respectively.

```
<deployment>
  <cluster hostcount="2" sitesperhost="4">
  </cluster>
</deployment>
```

Finally, as a shorthand, elements that do not contain any children can be entered without an ending tag by adding the slash to the end of the initial tag. In the following example, the `cluster`, `export`, and `heartbeat` tags use this form of shorthand:

```
<deployment>
  <cluster hostcount="2" sitesperhost="4"/>
  <export enabled="true"/>
  <heartbeat timeout="10"/>
</deployment>
```

For complete information about the XML standard and XML syntax, see the official XML site at <http://www.w3.org/XML/>.

E.2. The Structure of the Deployment File

The deployment file starts with the XML declaration. After the XML declaration, the root element of the deployment file is the `deployment` element. The remainder of the XML document consists of elements that are children of the `deployment` element.

Figure E.1, “Deployment XML Structure” shows the structure of the deployment file. The indentation indicates the hierarchical parent-child relationships of the elements and an ellipsis (...) shows where an element may appear multiple times.

Figure E.1. Deployment XML Structure

```

<deployment>
  <cluster/>
  <paths>
    <commandlog/>
    <commandlogsnapshot/>
    <exportoverflow/>
    <snapshots/>
    <voltdbroot/>
  </paths>
  <admin-mode/>
  <commandlog>
    <frequency/>
  </commandlog>
  <export>
    <onserver>
      <configuration>
        <property/>...
      </configuration>
    </onserver>
  </export>
  <heartbeat/>
  <httpd>
    <jsonapi/>
  </httpd>
  <partition-detection>
    <snapshot/>
  </partition-detection>
  <replication/>
  <security/>
  <snapshot/>
  <systemsettings>
    <temptables/>
    <snapshot/>
  </systemsettings>
  <users>
    <user/>...
  </users>
</deployment>

```

Table E.1, “Deployment File Elements and Attributes” provides further detail on the elements, including their relationships (as child or parent) and the allowable attributes for each.

Table E.1. Deployment File Elements and Attributes

Element	Child of	Parent of	Attributes
deployment*	(root element)	admin-mode, commandlog, cluster, export, heartbeat, httpd, partition-detection,	

Element	Child of	Parent of	Attributes
		paths, security, snapshot, systemsettings, users	
cluster [*]	deployment		hostcount={int} [*] sitesperhost={int} [*] elastic={enabled disabled} kfactor={int}
admin-mode	deployment		port={int} adminstartup={true false}
heartbeat	deployment		timeout={int} [*]
partition-detection	deployment	snapshot	enabled={true false}
snapshot [*]	partition-detection		prefix={text} [*]
commandlog	deployment	frequency	enabled={true false} synchronous={true false} logsize={int}
frequency	commandlog		time={int} transactions={int}
export	deployment	onserver	enabled={true false}
onserver	export	configuration	exportto={file jdbc custom} exportconnectorclass={class-name}
configuration [*]	onserver	property	
property	configuration		name={text} [*]
httpd	deployment	jsonapi	port={int} enabled={true false}
jsonapi	httpd		enabled={true false}
paths	deployment	exportoverflow, snapshots, voltdbroot	
commandlog	paths		path={directory-path} [*]
commandlogsnapshot	paths		path={directory-path} [*]
exportoverflow	paths		path={directory-path} [*]
snapshots	paths		path={directory-path} [*]
voltdbroot	paths		path={directory-path} [*]
replication	deployment		port={int}
security	deployment		enabled={true false}
snapshot	deployment		frequency={int}{s m h} [*] prefix={text} [*] retain={int} [*] enabled={true false}
systemsettings	deployment	snapshot, temptables	
snapshot	systemsettings		priority={int} [*]
temptables	systemsettings		maxsize={int} [*]
users	deployment	user	
user	users		name={text} [*]

Element	Child of	Parent of	Attributes
			password={ text} [*] roles={ role-name[,..]} ¹

^{*}Required

¹The attribute "groups" can be used in place of "roles" for backwards compatibility.

Appendix F. System Procedures

VoltDB provides system procedures that client applications can call to perform certain system-wide administrative functions. You invoke system procedures the same way you invoke other stored procedures, using the VoltDB client method `callProcedure`.

This appendix describes the following system procedures.

- `@AdHoc`
- `@Explain`
- `@ExplainProc`
- `@Pause`
- `@Promote`
- `@Quiesce`
- `@Resume`
- `@Shutdown`
- `@SnapshotDelete`
- `@SnapshotRestore`
- `@SnapshotSave`
- `@SnapshotScan`
- `@SnapshotStatus`
- `@Statistics`
- `@SystemCatalog`
- `@SystemInformation`
- `@UpdateApplicationCatalog`
- `@UpdateLogging`

@AdHoc

@AdHoc — Executes an SQL statement specified at runtime.

Syntax

`ClientResponse client.callProcedure("@AdHoc", String SQL-statement)`

Description

The @AdHoc system procedure lets you perform arbitrary SQL queries on a running VoltDB database.

You can execute multiple SQL queries in a single call to @AdHoc by separating the individual queries with semicolons. When you do this, the queries are performed as a single transaction. That is, the queries all succeed as a group or they all roll back if any of them fail.

Performance of ad hoc queries is optimized, where possible. However, it is important to note that ad hoc queries are not pre-compiled, like queries in stored procedures. Therefore, use of stored procedures is recommended over @AdHoc for frequent, repetitive, or performance-sensitive queries.

Return Values

Returns one VoltTable for each query, with as many rows as there are records returned by the query. The column names and datatypes match the names and datatypes of the fields returned by the query.

Example

The following example uses @AdHoc to execute an SQL SELECT statement and display the number of reservations for a specific customer in the flight reservation database.

```
try {
    VoltTable[] results = client.callProcedure("@AdHoc",
        "SELECT COUNT(*) FROM RESERVATION " +
        "WHERE CUSTOMERID=" + custid).getResults();
    System.out.printf("%d reservations found.\n",
        results[0].fetchRow(0).getLong(0));
}
catch (Exception e) {
    e.printStackTrace();
}
```

@Explain

@Explain — Returns the execution plan for the specified SQL query.

Syntax

```
ClientResponse client.callProcedure("@Explain", String SQL-statement)
```

Description

The @Explain system procedure evaluates the specified SQL query and returns the resulting execution plan. Execution, or explain, plans describe how VoltDB expects to execute the query at runtime, including what indexes are used, the order the tables are joined, and so on. Execution plans are useful for identifying performance issues in query design. See the chapter on execution plans in the *VoltDB Performance Guide* for information on how to interpret the plans.

Return Values

Returns one VoltTable with one row and one column.

Name	Datatype	Description
EXECUTION_PLAN	VARCHAR	The execution plan as text.

Example

The following example uses @Explain to evaluate an ad hoc SQL SELECT statement against the voter sample application.

```
try {
    String query = "SELECT COUNT(*) FROM CONTESTANTS;";
    VoltTable[] results = client.callProcedure("@Explain",
        query ).getResults();
    System.out.printf("Query: %d\nPlan:\n%d",
        query, results[0].fetchRow(0).getString(0));
}
catch (Exception e) {
    e.printStackTrace();
}
```

@ExplainProc

@ExplainProc — Returns the execution plans for all SQL queries in the specified stored procedure.

Syntax

```
ClientResponse client.callProcedure("@ExplainProc", String procedure-name)
```

Description

The @ExplainProc system procedure returns the execution plans for all of the SQL queries within the specified stored procedure. Execution, or explain, plans describe how VoltDB expects to execute the queries at runtime, including what indexes are used, the order the tables are joined, and so on. Execution plans are useful for identifying performance issues in query and stored procedure design. See the chapter on execution plans in the *VoltDB Performance Guide* for information on how to interpret the plans.

Return Values

Returns one VoltTable with one row for each query in the stored procedure.

Name	Datatype	Description
SQL_STATEMENT	VARCHAR	The SQL query.
EXECUTION_PLAN	VARCHAR	The execution plan as text.

Example

The following example uses @ExplainProc to evaluate the execution plans associated with the ContestantWinningStates stored procedure in the voter sample application.

```
try {
    VoltTable[] results = client.callProcedure("@ExplainProc",
        "voter.procedures.ContestantWinningStates" ).getResults();
    results[0].resetRowPosition();
    while (results[0].advanceRow()) {
        System.out.printf("Query: %d\nPlan:\n%d",
            results[0].getString(0), results[0].getString(1));
    }
}
catch (Exception e) {
    e.printStackTrace();
}
```

@Pause

@Pause — Initiates admin mode on the cluster.

Syntax

```
ClientResponse client.callProcedure("@Pause")
```

Description

The @Pause system procedure initiates admin mode on the cluster. In admin mode, no further transaction requests are accepted from clients on the client port. All interactions with a database in admin mode must occur through the admin port specified in the deployment file.

There may be existing transactions still in the queue after admin mode is initiated. Until these transactions are completed, the database is not entirely paused. You can use the @Statistics system procedure with the "LIVECLIENTS" keyword to determine how many transactions are outstanding for each client connection.

The goal of admin mode is to pause the system and ensure no further changes to the database can occur when performing sensitive administrative operations, such as taking a snapshot before shutting down.

Several important points to consider concerning @Pause are:

- @Pause must be called through the admin port, not the standard client port.
- Although new stored procedure invocations received on the client port are rejected in admin mode, existing connections from client applications are not removed.
- However, if export is enabled when admin mode is invoked, any connection from an export client to the client port is terminated and further connections refused. The export client will attempt to reconnect until normal operations are resumed and the connection is re-established. Export clients connected to the admin port are not affected.
- To return to normal database operation, you must call the system procedure @Resume on the admin port.

Return Values

Returns one VoltTable with one row.

Name	Datatype	Description
STATUS	BIGINT	Always returns the value zero (0) indicating success.

Example

The following example, if called through the admin port, initiates admin mode on the database cluster.

```
client.callProcedure("@Pause");
```

@Promote

@Promote — Promotes a replica database to normal operation.

Syntax

```
ClientResponse client.callProcedure("@Promote")
```

Description

The @Promote system procedure promotes a replica database to normal operation. During database replication, the replica database only accepts input from the database replication (DR) agent. If, for any reason, the master database fails and replication stops, you can use @Promote to change the replica database from a replica to a normal database. When you invoke the @Promote system procedure, the replica exits read-only mode and becomes a fully operational VoltDB database that can receive and execute both read-only and read/write queries.

Note that once a database is promoted, it cannot return to its original role as the receiving end of database replication without first stopping and reinitializing the database as a replica. If the database is *not* a replica, invoking @Promote returns an error.

Return Values

Returns one VoltTable with one row.

Name	Datatype	Description
STATUS	BIGINT	Always returns the value zero (0) indicating success.

Example

The following example promotes a database cluster.

```
client.callProcedure("@Promote");
```


@Quiesce

@Quiesce — Waits for all queued export data to be written to the connector.

Syntax

```
ClientResponse client.callProcedure("@Quiesce")
```

Description

The @Quiesce system procedure waits for any queued export data to be written to the export connector before returning to the calling application. @Quiesce also does an fsync to ensure any pending export overflow is written to disk. This system procedure should be called after stopping client applications and before calling @Shutdown to ensure that all export activity is concluded before shutting down the database.

If export is not enabled, the procedure returns immediately.

Return Values

Returns one VoltTable with one row.

Name	Datatype	Description
STATUS	BIGINT	Always returns the value zero (0) indicating success.

Example

The following example uses drain and @Quiesce to complete any asynchronous transactions and clear the export queues before shutting down the database.

```
// Complete all outstanding activities
try {
    client.drain();
    client.callProcedure("@Quiesce");
}
catch (Exception e) {
    e.printStackTrace();
}

// Shutdown the database.
try {
    client.callProcedure("@Shutdown");
}

// We expect an exception when the connection drops.
// Report any other exception.
catch (org.voltdb.client.ProcCallException e) { }
catch (Exception e) { e.printStackTrace(); }
```

@Resume

@Resume — Returns a paused database to normal operating mode.

Syntax

```
ClientResponse client.callProcedure("@Resume")
```

Description

The @Resume system procedure switches all nodes in a database cluster from admin mode to normal operating mode. In other words, @Resume is the opposite of @Pause.

After calling this procedure, the cluster returns to accepting new connections and stored procedure invocations from clients connected to the standard client port. If any export clients connected to the client port were disconnected by @Pause, they will automatically reconnect and restart export processing once @Resume restores normal operation.

@Resume must be invoked from a connection to the admin port.

Return Values

Returns one VoltTable with one row.

Name	Datatype	Description
STATUS	BIGINT	Always returns the value zero (0) indicating success.

Example

The following example uses @Resume to return the cluster to normal operation.

```
client.callProcedure("@Resume");
```

@Shutdown

@Shutdown — Shuts down the database.

Syntax

```
ClientResponse client.callProcedure("@Shutdown")
```

Description

The @Shutdown system procedure performs an orderly shut down of a VoltDB database on all nodes of the cluster.

VoltDB is an in-memory database. By default, data is not saved when you shut down the database. If you want to save the data between sessions, you can enable command logging or save a snapshot (either manually or using automated snapshots) before the shutdown. See Chapter 10, *Command Logging and Recovery* and Chapter 9, *Saving & Restoring a VoltDB Database* for more information.

Note that once the database shuts down, the client connection is lost and the calling program cannot make any further requests to the server.

Example

The following example uses @Shutdown to stop the database cluster. Note the use of catch to separate out a VoltDB call procedure exception (which is expected) from any other exception.

```
try {
    client.callProcedure("@Shutdown");
}

    // we expect an exception when the connection drops.
catch (org.voltdb.client.ProcCallException e) {
    System.out.println("Database shutdown initiated.");
}

    // report any other exception.
catch (Exception e) {
    e.printStackTrace();
}
```

@SnapshotDelete

@SnapshotDelete — Deletes one or more native snapshots.

Syntax

```
ClientResponse client.callProcedure("@SnapshotDelete", String[] directory-paths, String[]
Unique-IDs)
```

Description

The @SnapshotDelete system procedure deletes native snapshots from the database cluster. This is a cluster-wide operation and a single invocation will remove the snapshot files from all of the nodes.

The procedure takes two additional parameters: a String array of directory paths and a String array of unique IDs (prefixes).

The two arrays are read as a series of value pairs, so that the first element of the directory path array and the first element of the unique ID array will be used to identify the first snapshot to delete. The second element of each array will identify the second snapshot to delete. And so on.

@SnapshotDelete can delete native format snapshots only. The procedure cannot delete CSV format snapshots.

Return Values

Returns one VoltTable with a row for every snapshot file affected by the operation.

Name	Datatype	Description
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
PATH	STRING	The directory path where the snapshot file resides.
NONCE	STRING	The unique identifier for the snapshot.
NAME	STRING	The file name.
SIZE	BIGINT	The total size, in bytes, of the file.
DELETED	STRING	String value indicating whether the file was successfully deleted ("TRUE") or not ("FALSE").
RESULT	STRING	String value indicating the success ("SUCCESS") or failure ("FAILURE") of the request.
ERR_MSG	STRING	If the result is FAILURE, this column contains a message explaining the cause of the failure.

Example

The following example uses @SnapshotScan to identify all of the snapshots in the directory /tmp/volt-db/backup/. This information is then used by @SnapshotDelete to delete those snapshots.

```
try {
```

```
        results = client.callProcedure("@SnapshotScan",
                                      "/tmp/voltdb/backup/").getResults();
    }
    catch (Exception e) { e.printStackTrace(); }

    VoltTable table = results[0];
    int numofsnapshots = table.getRowCount();
    int i = 0;

    if (numofsnapshots > 0) {
        String[] paths = new String[numofsnapshots];
        String[] nonces = new String[numofsnapshots];
        for (i=0;i<numofsnapshots;i++) { paths[i] = "/etc/voltdb/backup/"; }
        table.resetRowPosition();
        i = 0;
        while (table.advanceRow()) {
            nonces[i] = table.getString("NONCE");
            i++;
        }

        try {
            client.callProcedure("@SnapshotDelete",paths,nonces);
        }
        catch (Exception e) { e.printStackTrace(); }
    }
}
```

@SnapshotRestore

@SnapshotRestore — Restores a database from disk using a native format snapshot.

Syntax

```
ClientResponse client.callProcedure("@SnapshotRestore", String directory-path, String unique-ID)
```

Description

The @SnapshotRestore system procedure restores a previously saved database from disk to memory. The snapshot must be in native format. (You cannot restore a CSV format snapshot using @SnapshotRestore.) The restore request is propagated to all nodes of the cluster, so a single call to @SnapshotRestore will restore the entire database cluster.

The second parameter, *directory-path*, specifies where VoltDB looks for the snapshot files.

The third argument, *unique-ID*, is a unique identifier that is used as a filename prefix to distinguish between multiple snapshots.

You can perform only one restore operation on a running VoltDB database. Subsequent attempts to call @SnapshotRestore result in an error. Note that this limitation applies to both manual and automated restores. Since command logging often includes snapshots, you should never perform a manual @SnapshotRestore after recovering a database using command logs.

See Chapter 9, *Saving & Restoring a VoltDB Database* for more information about saving and restoring VoltDB databases.

Return Values

Returns one VoltTable with a row for every table restored at each execution site.

Name	Datatype	Description
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
SITE_ID	INTEGER	Numeric ID of the execution site on the host node.
TABLE	STRING	The name of the table being restored.
PARTITION_ID	INTEGER	The numeric ID for the logical partition that this site represents. When using a K value greater than zero, there are multiple copies of each logical partition.
RESULT	STRING	String value indicating the success ("SUCCESS") or failure ("FAILURE") of the request.
ERR_MSG	STRING	If the result is FAILURE, this column contains a message explaining the cause of the failure.

Example

The following example uses @SnapshotRestore to restore previously saved database content from the path `/tmp/voltdb/backup/` using the unique identifier *flight*.

Since there are a number of situations that impact what data is restored, it is a good idea to review the return values to see what tables and partitions were affected. In the example, the contents of the VoltTable array is written to standard output so the operator can confirm that the restore completed as expected.

```
VoltTable[] results = null;

try {
    results = client.callProcedure("@SnapshotRestore",
                                   "/tmp/voltdb/backup/",
                                   "flight").getResults();
}
catch (Exception e) {
    e.printStackTrace();
}

for (int t=0; t<results.length; t++) {
    VoltTable table = results[t];
    for (int r=0; r<table.getRowCount(); r++) {
        VoltTableRow row = table.fetchRow(r);
        System.out.printf("Node %d Site %d restoring " +
                           "table %s partition %d.\n",
                           row.getLong("HOST_ID"), row.getLong("SITE_ID"),
                           row.getString("TABLE"), row.getLong("PARTITION"));
    }
}
```

@SnapshotSave

@SnapshotSave — Saves the current database contents to disk.

Syntax

```
ClientResponse client.callProcedure("@SnapshotSave", String directory-path, String unique-ID,
Integer blocking-flag)
```

```
ClientResponse client.callProcedure("@SnapshotSave", String json-encoded-options)
```

Description

The @SnapshotSave system procedure saves the contents of the current in-memory database to disk. Each node of the database cluster saves its portion of the database locally.

There are two forms of the @SnapshotSave stored procedure: a procedure call with individual argument parameters and a procedure call with all arguments in a single JSON-encoded string. When you specify the system procedure arguments as individual parameters, VoltDB creates a native mode snapshot that can be used to recover or restore the database. When you specify the arguments as a JSON-encoded string, you can request a different format for the snapshot, including CSV (comma-separated value) files that can be used for import into other databases or utilities.

Individual Arguments

When you specify the system procedure arguments as individual parameters, you must specify three arguments:

1. The directory path where the snapshot files are stored
2. An identifier that is included in the file names to uniquely identify the files that make up a single snapshot
3. A flag value indicating whether the snapshot should block other transactions until it is complete or not

The resulting snapshot consists of multiple files saved to the directory specified by *directory-path* using *unique-ID* as a filename prefix. The third argument, *blocking-flag*, specifies whether the save is performed synchronously (thereby blocking any following transactions until the save completes) or asynchronously. If this parameter is set to any non-zero value, the save operation will block any following transactions. If it is zero, others transactions will be executed in parallel.

The files created using this invocation are in native VoltDB snapshot format and can be used to restore or recover the database at some later time. This is the same format used for automatic snapshots. See Chapter 9, *Saving & Restoring a VoltDB Database* for more information about saving and restoring VoltDB databases.

JSON-Encoded Arguments

When you specify the system procedure arguments as a JSON-encoded string, you can specify what snapshot format you want to create. Table F.1, “@SnapshotSave Options” describes all possible options when creating a snapshot using JSON-encoded arguments.

Table F.1. @SnapshotSave Options

Option	Description
uripath	Specifies the path where the snapshot files are created. Note that, as a JSON-encoded argument, the path must be specified as a URI, not just a system directory path. Therefore, a local directory must be specified using the <code>file://</code> identifier, such as <code>"file:///tmp"</code> , and the path must exist on all nodes of the cluster.
nonce	Specifies the unique identifier for the snapshot.
block	Specifies whether the snapshot should be synchronous (true) and block other transactions or asynchronous (false).
format	<p>Specifies the format of the snapshot. Valid formats are "csv" and "native".</p> <p>When you save a snapshot in CSV format, the resulting files are in standard comma-separated value format, with only one file for each table. In other words, duplicates (from replicated tables or duplicate partitions due to K-safety) are eliminated. CSV formatted snapshots are useful for import or reuse by other databases or utilities. However, they <i>cannot</i> be used to restore or recover a VoltDB database.</p> <p>When you save a snapshot in native format, each node and partition saves its contents to separate files. These files can then be used to restore or recover the database. It is also possible to later convert native format snapshots to CSV using the snapshot utilities described in the <i>VoltDB Management Guide</i>.</p>

For example, the JSON-encoded arguments to synchronously save a CSV formatted snapshot to /tmp using the unique identifier "mydb" is the following:

```
{uripath:"file:///tmp",nonce:"mydb",block:true,format:"csv"}
```

The block and format arguments are optional. If you do not specify them they default to `block:false` and `format:"native"`. The arguments `uripath` and `nonce` are required.

Because the unique identifier is used in the resulting filenames, the identifier can contain only characters that are valid for Linux file names. In addition, hyphens ("-") and commas (",") are not permitted.

Note that it is normal to perform manual saves synchronously, to ensure the snapshot represents a known state of the database. However, automatic snapshots are performed asynchronously to reduce the impact on ongoing database activity.

Return Values

The @SnapshotSave system procedure returns two different VoltTables, depending on the outcome of the request.

Option #1: one VoltTable with a row for every execution site. (That is, the number of hosts multiplied by the number of sites per host.).

Name	Datatype	Description
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
SITE_ID	INTEGER	Numeric ID of the execution site on the host node.
RESULT	STRING	String value indicating the success ("SUCCESS") or failure ("FAILURE") of the request.

Name	Datatype	Description
ERR_MSG	STRING	If the result is FAILURE, this column contains a message explaining the cause of the failure.

Option #2: one VoltTable with a variable number of rows.

Name	Datatype	Description
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
TABLE	STRING	The name of the database table. The contents of each table is saved to a separate file. Therefore it is possible for the snapshot of each table to succeed or fail independently.
RESULT	STRING	String value indicating the success ("SUCCESS") or failure ("FAILURE") of the request.
ERR_MSG	STRING	If the result is FAILURE, this column contains a message explaining the cause of the failure.

Example

The following example uses @SnapshotSave to save the current database content in native snapshot format to the path /tmp/voltdb/backup/ using the unique identifier *flight* on each node of the cluster.

Note that the procedure call will return successfully even if the save was not entirely successful. The information returned in the VoltTable array tells you what parts of the operation were successful or not. For example, save may succeed on one node but not on another.

The following example checks the return values and notifies the operator when portions of the save operation are not successful.

```
VoltTable[] results = null;

try { results = client.callProcedure("@SnapshotSave",
                                     "/tmp/voltdb/backup/",
                                     "flight", 1).getResults();
}
catch (Exception e) {e.printStackTrace(); }

for (int table=0; table<results.length; table++) {
    for (int r=0;r<results[table].getRowCount();r++) {
        VoltTableRow row = results[table].fetchRow(r);
        if (row.getString("RESULT").compareTo("SUCCESS") != 0) {
            System.out.printf("Site %s failed to write " +
                              "table %s because %s.\n",
                              row.getString("HOSTNAME"), row.getString("TABLE"),
                              row.getString("ERR_MSG"));
        }
    }
}
```

@SnapshotScan

@SnapshotScan — Lists information about existing native snapshots in a given directory path.

Syntax

```
ClientResponse client.callProcedure("@SnapshotScan", String directory-path)
```

Description

The @SnapshotScan system procedure provides information about any native snapshots that exist within the specified directory path for all nodes on the cluster. The procedure reports the name (prefix) of the snapshot, when it was created, how long it took to create, and the size of the individual files that make up the snapshot(s).

@SnapshotScan does not include CSV format snapshots in its output. Only native format snapshots are listed.

Return Values

On successful completion, this system procedure returns three VoltTables providing the following information:

- A summary of the snapshots found
- Available space in the directories scanned
- Details concerning the Individual files that make up the snapshots

The first table contains one row for every snapshot found.

Name	Datatype	Description
PATH	STRING	The directory path where the snapshot resides.
NONCE	STRING	The unique identifier for the snapshot.
TXNID	BIGINT	The transaction ID of the snapshot.
CREATED	BIGINT	The timestamp when the snapshot was created (in milliseconds).
SIZE	BIGINT	The total size, in bytes, of all the snapshot data.
TABLES_REQUIRED	STRING	A comma-separated list of all the table names listed in the snapshot digest file. In other words, all of the tables that make up the snapshot.
TABLES_MISSING	STRING	A comma-separated list of database tables for which no data can be found. (That is, the corresponding files are missing or unreadable.)
TABLES_INCOMPLETE	STRING	A comma-separated list of database tables with only partial data saved in the snapshot. (That is, data from some partitions is missing.)
COMPLETE	STRING	A string value indicating whether the snapshot as a whole is complete ("TRUE") or incomplete ("FALSE"). If this col-

Name	Datatype	Description
		umn is "FALSE", the preceding two columns provide additional information concerning what is missing.

The second table contains one row for every host.

Name	Datatype	Description
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
PATH	STRING	The directory path specified in the call to the procedure.
TOTAL	BIGINT	The total space (in bytes) on the device.
FREE	BIGINT	The available free space (in bytes) on the device.
USED	BIGINT	The total space currently in use (in bytes) on the device.
RESULT	STRING	String value indicating the success ("SUCCESS") or failure ("FAILURE") of the request.
ERR_MSG	STRING	If the result is FAILURE, this column contains a message explaining the cause of the failure.

The third table contains one row for every file in the snapshot collection.

Name	Datatype	Description
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
PATH	STRING	The directory path where the snapshot file resides.
NAME	STRING	The file name.
TXNID	BIGINT	The transaction ID of the snapshot.
CREATED	BIGINT	The timestamp when the snapshot was created (in milliseconds).
TABLE	STRING	The name of the database table the data comes from.
COMPLETED	STRING	A string indicating whether all of the data was successfully written to the file ("TRUE") or not ("FALSE").
SIZE	BIGINT	The total size, in bytes, of the file.
IS_REPLICATED	STRING	A string indicating whether the table in question is replicated ("TRUE") or partitioned ("FALSE").
PARTITIONS	STRING	A comma-separated string of partition (or site) IDs from which data was taken during the snapshot. For partitioned tables where there are multiple sites per host, there can be data from multiple partitions in each snapshot file. For replicated tables, data from only one copy (and therefore one partition) is required.
TOTAL_PARTITIONS	BIGINT	The total number of partitions from which data was taken.
READABLE	STRING	A string indicating whether the file is accessible ("TRUE") or not ("FALSE").
RESULT	STRING	String value indicating the success ("SUCCESS") or failure ("FAILURE") of the request.

Name	Datatype	Description
ERR_MSG	STRING	If the result is FAILURE, this column contains a message explaining the cause of the failure.

If the system procedure fails because it cannot access the specified path, it returns a single VoltTable with one row and one column.

Name	Datatype	Description
ERR_MSG	STRING	A message explaining the cause of the failure.

Example

The following example uses @SnapshotScan to list information about the snapshots in the directory /tmp/voltdb/backup/.

In the return value, the first VoltTable in the array lists the snapshots and certain status information. The second element of the array provides information about the directory itself (such as used, free, and total disk space). The third element of the array lists specific information about the individual files in the snapshot(s).

```
VoltTable[] results = null;

try { results = client.callProcedure("@SnapshotScan",
                                     "/tmp/voltdb/backup/").getResults();
}
catch (Exception e) { e.printStackTrace(); }

for (VoltTable t: results) {
    System.out.println(t.toString());
}
```

@SnapshotStatus

@SnapshotStatus — Lists information about the most recent snapshots created from the current database.

Syntax

```
ClientResponse client.callProcedure("@SnapshotStatus")
```

Description

Warning

The @SnapshotStatus system procedure is being deprecated and may be removed in future versions. Please use the @Statistics "SNAPSHOTSTATUS" selector, which returns the same results, to retrieve information about recent snapshots.

The @SnapshotStatus system procedure provides information about up to ten of the most recent snapshots performed on the current database. The information provided includes the directory path and prefix for the snapshot, when it occurred and how long it took, as well as whether the snapshot was completed successfully or not.

@SnapshotStatus provides status of any snapshots, including both native and CSV snapshots, as well as manual, automated, and command log snapshots.

Note that @SnapshotStatus does not tell you whether the snapshot files still exist, only that the snapshot was performed. You can use the procedure @SnapshotScan to determine what snapshots are available.

Also, the status information is reset each time the database is restarted. In other words, @SnapshotStatus only provides information about the most recent snapshots since the current database instance was started.

Return Values

Returns one VoltTable with a row for every snapshot file in the recent snapshots performed on the cluster.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the snapshot was initiated (in milliseconds).
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
TABLE	STRING	The name of the database table whose data the file contains.
PATH	STRING	The directory path where the snapshot file resides.
FILENAME	STRING	The file name.
NONCE	STRING	The unique identifier for the snapshot.
TXNID	BIGINT	The transaction ID of the snapshot.
START_TIME	BIGINT	The timestamp when the snapshot began (in milliseconds).
END_TIME	BIGINT	The timestamp when the snapshot was completed (in milliseconds).

Name	Datatype	Description
SIZE	BIGINT	The total size, in bytes, of the file.
DURATION	BIGINT	The length of time (in milliseconds) it took to complete the snapshot.
THROUGHPUT	FLOAT	The average number of bytes per second written to the file during the snapshot process.
RESULT	STRING	String value indicating whether the writing of the snapshot file was successful ("SUCCESS") or not ("FAILURE").

Example

The following example uses @SnapshotStatus to display information about most recent snapshots performed on the current database.

```
VoltTable[] results = null;

try {
    results = client.callProcedure("@SnapshotStatus").getResults();
}
catch (Exception e) { e.printStackTrace(); }

for (VoltTable t: results) {
    System.out.println(t.toString());
}
```

@Statistics

@Statistics — Returns statistics about the usage of the VoltDB database.

Syntax

```
ClientResponse client.callProcedure("@Statistics", String component, Integer delta-flag)
```

Description

The @Statistics system procedure returns information about the VoltDB database. The second argument, *component*, specifies what aspect of VoltDB to return statistics about. The following are the allowable values of *component*:

"DR"	Returns information about the status of database replication, including how much data is waiting to be sent to the DR agent. This information is available only if the database is licensed for database replication.
"INDEX"	Returns information about the indexes in the database, including the number of keys for each index and the estimated amount of memory used to store those keys. Separate information is returned for each partition in the database.
"INITIATOR"	Returns information on the number of procedure invocations for each stored procedure (including system procedures). The count of invocations is reported for each connection to the database.
"IOSTATS"	Returns information on the number of messages and amount of data (in bytes) sent to and from each connection to the database.
"LIVECLIENTS"	Returns information about the number of outstanding requests per client. You can use this information to determine how much work is waiting in the execution queues.
"MANAGEMENT"	Returns the same information as INDEX, INITIATOR, IOSTATS, MEMORY, PROCEDURE, and TABLE, except all in a single procedure call.
"MEMORY"	Returns statistics on the use of memory for each node in the cluster. MEMORY statistics include the current resident set size (RSS) of the VoltDB server process; the amount of memory used for Java temporary storage, database tables, indexes, and string (including varbinary) storage; as well as other information.
"PARTITIONCOUNT"	Returns information on the number of unique partitions in the cluster. The VoltDB cluster creates multiple partitions based on the number of servers and the number of sites per host requested. So, for example, a 2 node cluster with 4 sites per host will have 8 partitions. However, when you define a cluster with K-safety, there are duplicate partitions. PARTITIONCOUNT only reports the number of unique partitions available in the cluster.
"PLANNER"	Returns information on the use of cached plans within each partition. Queries in stored procedures are planned when the application catalog is compiled.

However, ad hoc queries must be planned at runtime. To improve performance, VoltDB caches plans for ad hoc queries so they can be reused when a similar query is encountered later. There are two caches: the level 1 cache performs exact matches on queries and the level 2 cache parameterizes constants so it can match queries with the same plan but different input. The planner statistics provide information about the size of each cache, how frequently it is used, and the minimum, maximum, and average execution time of ad hoc queries as a result.

"PROCEDURE"	Returns information on the usage of stored procedures for each site within the database cluster sorted by partition. The information includes the name of the procedure, the number of invocations (for each site), and selected performance information on minimum, maximum, and average execution time.
"PROCEDURE-PROFILE"	Returns summary information on the usage of stored procedures averaged across all partitions in the cluster. The information from PROCEDURE-PROFILE is similar to the information from PROCEDURE, except it focuses on the performance of the individual procedures rather than on procedures by partition. The weighted average across partitions is helpful for determining which stored procedures the application is spending most of its time in.
"SNAPSHOTSTATUS"	Returns information about up to ten of the most recent snapshots performed by the database. The results include the directory path and prefix for the snapshot, when it occurred, how long it took, and whether the snapshot was completed successfully or not. The results report on both native and CSV snapshots, as well as manual, automated, and command log snapshots. Note that this selector does not tell you whether the snapshot files still exist, only that the snapshot was performed. Use the @SnapshotScan procedure to determine what snapshots are available.
"TABLE"	Returns information about the database tables, including the number of rows per site for each table. This information can be useful for seeing how well the rows are distributed across the cluster for partitioned tables.

Note that INITIATOR and PROCEDURE report information on both user-declared stored procedures and system procedures. These include certain system procedures that are used internally by VoltDB and are not intended to be called by client applications. Only the system procedures documented in this appendix are intended for client invocation.

The third argument, *delta-flag*, specifies whether statistics are reported from when the database started or since the last call to @Statistics where the flag was set. If the delta-flag is set to zero, the system procedure returns statistics since the database started. If the delta-flag is non-zero, the system procedure returns statistics for the interval since the last time @Statistics was called with a non-zero flag. (If @Statistics has not been called with a non-zero flag before, the first call with the flag set returns statistics since startup.)

Return Values

Returns different VoltTables depending on which component is requested. The following tables identify the structure of the return values for each component. (Note that the MANAGEMENT component returns seven VoltTables.)

DR — Returns two VoltTables. The first table contains information about the replication streams, which consist of a row per partition for each server. The data shows the current state of replication and how much data is currently queued for the DR agent.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the information was collected (in milliseconds).
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
PARTITION_ID	INTEGER	The numeric ID for the logical partition.
STREAMTYPE	STRING	The type of stream, which can either be "TRANSACTIONS" or "SNAPSHOT".
TOTALBYTES	BIGINT	The total number of bytes currently queued for transmission to the DR agent.
TOTALBYTESIN MEMORY	BIGINT	The total number of bytes of queued data currently held in memory. If the amount of total bytes is larger than the amount in memory, the remainder is kept in overflow storage on disk.
TOTALBUFFERS	BIGINT	The total number of buffers in this partition currently waiting for acknowledgement from the DR agent. Partitions create a buffer every five milliseconds.
LASTACKTIMESTAMP	BIGINT	The timestamp of the last acknowledgement received from the DR agent.
ISSYNCD	STRING	A text string indicating whether the database is currently being replicated. If replication has not started, or the overflow capacity has been exceeded (that is, replication has failed), the value of ISSYNCD is "false". If replication is currently in progress, the value is "true".
MODE	STRING	A text string indicating whether this particular partition is replicating data for the DR agent ("NORMAL") or not ("PAUSED"). Only one copy of each logical partition actually sends data to the DR agent during replication. So for clusters with a K-safety value greater than zero, not all physical partitions will report "NORMAL" even when replication is in progress.

The second table returns a row for every host in the cluster, showing whether a replication snapshot is in progress and if it is, the status of transmission to the DR agent.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the information was collected (in milliseconds).
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
ENABLED	STRING	A text string indicating whether the database is currently being replicated. Possible values are "true" and "false".
SYNCSNAPSHOTSTATE	STRING	A text string indicating the current state of the synchronization snapshot that begins replication. During normal operation, this value is "NOT_SYNCING" indicating either that replication is not active or that transactions are actively being replicated. If a synchronization snapshot is in progress,

Name	Datatype	Description
		this value provides additional information about the specific activity underway.
ROWSINSYNC SNAPSHOT	BIGINT	Reserved for future use.
ROWSACKEDFORSYNC SNAPSHOT	BIGINT	Reserved for future use.

INDEX — Returns a row for every index in every execution site.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the information was collected (in milliseconds).
HOST_ID	BIGINT	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
SITE_ID	BIGINT	Numeric ID of the execution site on the host node.
PARTITION_ID	BIGINT	The numeric ID for the logical partition that this site represents. When using a K value greater than zero, there are multiple copies of each logical partition.
INDEX_NAME	STRING	The name of the index.
TABLE_NAME	STRING	The name of the database table to which the index applies.
INDEX_TYPE	STRING	A text string identifying the type of the index as either a hash or tree index and whether it is unique or not. Possible values include the following: CompactingHashMultiMapIndex CompactingHashUniqueIndex CompactingTreeMultiMapIndex CompactingTreeUniqueIndex
IS_UNIQUE	TINYINT	A byte value specifying whether the index is unique (1) or not (0).
IS_COUNTABLE	TINYINT	A byte value specifying whether the index maintains a counter to optimize COUNT(*) queries.
ENTRY_COUNT	BIGINT	The number of index entries currently in the partition.
MEMORY_ESTIMATE	INTEGER	The estimated amount of memory (in kilobytes) consumed by the current index entries.

INITIATOR — Returns a separate row for each connection and the stored procedures initiated by that connection.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the information was collected (in milliseconds).
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
SITE_ID	INTEGER	Numeric ID of the execution site on the host node.

Name	Datatype	Description
CONNECTION_ID	BIGINT	Numeric ID of the client connection invoking the procedure.
CONNECTION_HOST_NAME	STRING	The server name of the node from which the client connection originates.
PROCEDURE_NAME	STRING	The name of the stored procedure.
INVOCATIONS	BIGINT	The number of times the stored procedure has been invoked by this connection on this host node.
AVG_EXECUTION_TIME	INTEGER	The average length of time (in milliseconds) it took to execute the stored procedure.
MIN_EXECUTION_TIME	INTEGER	The minimum length of time (in milliseconds) it took to execute the stored procedure.
MAX_EXECUTION_TIME	INTEGER	The maximum length of time (in milliseconds) it took to execute the stored procedure.
ABORTS	BIGINT	The number of times the procedure was aborted.
FAILURES	BIGINT	The number of times the procedure failed unexpectedly. (As opposed to user aborts or expected errors, such as constraint violations.)

IOSTATS — Returns one row for every client connection on the cluster.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the information was collected (in milliseconds).
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
CONNECTION_ID	BIGINT	Numeric ID of the client connection invoking the procedure.
CONNECTION_HOST_NAME	STRING	The server name of the node from which the client connection originates.
BYTES_READ	BIGINT	The number of bytes of data sent from the client to the host.
MESSAGES_READ	BIGINT	The number of individual messages sent from the client to the host.
BYTES_WRITTEN	BIGINT	The number of bytes of data sent from the host to the client.
MESSAGES_WRITTEN	BIGINT	The number of individual messages sent from the host to the client.

LIVECLIENTS — Returns a row for every client connection currently active on the cluster.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the information was collected (in milliseconds).
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
CONNECTION_ID	BIGINT	Numeric ID of the client connection invoking the procedure.

Name	Datatype	Description
CLIENT_HOSTNAME	STRING	The server name of the node from which the client connection originates.
ADMIN	TINYINT	A byte value specifying whether the connection is to the client port (0) or the admin port (1).
OUTSTANDING_REQUEST_BYTES	BIGINT	The number of bytes of data sent from the client currently pending on the host.
OUTSTANDING_RESPONSE_MESSAGES	BIGINT	The number of messages on the host queue waiting to be retrieved by the client.
OUTSTANDING_TRANSACTIONS	BIGINT	The number of transactions (that is, stored procedures) initiated on behalf of the client that have yet to be completed.

MEMORY — Returns a row for every server in the cluster.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the information was collected (in milliseconds).
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
RSS	INTEGER	The current resident set size. That is, the total amount of memory allocated to the VoltDB processes on the server.
JAVAUSED	INTEGER	The amount of memory (in kilobytes) allocated by Java and currently in use by VoltDB.
JAVAUNUSED	INTEGER	The amount of memory (in kilobytes) allocated by Java but unused. (In other words, free space in the Java heap.)
TUPLEDATA	INTEGER	The amount of memory (in kilobytes) currently in use for storing database records.
TUPLEALLOCATED	INTEGER	The amount of memory (in kilobytes) allocated for the storage of database records (including free space).
INDEXMEMORY	INTEGER	The amount of memory (in kilobytes) currently in use for storing database indexes.
STRINGMEMORY	INTEGER	The amount of memory (in kilobytes) currently in use for storing string and binary data that is not stored "in-line" in the database record.
TUPLECOUNT	BIGINT	The total number of database records currently in memory.
POOLEDMEMORY	BIGINT	The total size of memory (in megabytes) allocated for tasks other than database records, indexes, and strings. (For example, pooled memory is used for temporary tables while processing stored procedures.)

PARTITIONCOUNT — Returns one row identifying the total number of partitions and the host that provided that information.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the information was collected (in milliseconds).

Name	Datatype	Description
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
PARTITION_COUNT	INTEGER	The number of unique or logical partitions on the cluster. When using a K value greater than zero, there are multiple copies of each logical partition.

PLANNER — Returns a row for every planner cache. That is, one cache per execution site, plus one global cache per server. (The global cache is identified by a site and partition ID of minus one.)

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the information was collected (in milliseconds).
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
SITE_ID	INTEGER	Numeric ID of the execution site on the host node.
PARTITION_ID	INTEGER	The numeric ID for the logical partition that this site represents. When using a K value greater than zero, there are multiple copies of each logical partition.
CACHE1_LEVEL	INTEGER	The number of query plans in the level 1 cache.
CACHE2_LEVEL	INTEGER	The number of query plans in the level 2 cache.
CACHE1_HITS	INTEGER	The number of queries that matched and reused a plan in the level 1 cache.
CACHE2_HITS	INTEGER	The number of queries that matched and reused a plan in the level 2 cache.
CACHE_MISSES	INTEGER	The number of queries that had no match in the cache and had to be planned from scratch
PLAN_TIME_MIN	BIGINT	The minimum length of time (in nanoseconds) it took to complete the planning of ad hoc queries.
PLAN_TIME_MAX	BIGINT	The maximum length of time (in nanoseconds) it took to complete the planning of ad hoc queries.
PLAN_TIME_AVG	BIGINT	The average length of time (in nanoseconds) it took to complete the planning of ad hoc queries.
FAILURES	BIGINT	The number of times planning for an ad hoc query failed.

PROCEDURE — Returns a row for every stored procedure that has been executed on the cluster, grouped by execution site.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the information was collected (in milliseconds).
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
SITE_ID	INTEGER	Numeric ID of the execution site on the host node.

Name	Datatype	Description
PARTITION_ID	INTEGER	The numeric ID for the logical partition that this site represents. When using a K value greater than zero, there are multiple copies of each logical partition.
PROCEDURE	STRING	The class name of the stored procedure.
INVOCATIONS	BIGINT	The total number of invocations of this procedure at this site.
TIMED_INVOCATIONS	BIGINT	The number of invocations used to measure the minimum, maximum, and average execution time.
MIN_EXECUTION_TIME	BIGINT	The minimum length of time (in nanoseconds) it took to execute the stored procedure.
MAX_EXECUTION_TIME	BIGINT	The maximum length of time (in nanoseconds) it took to execute the stored procedure.
AVG_EXECUTION_TIME	BIGINT	The average length of time (in nanoseconds) it took to execute the stored procedure.
MIN_RESULT_SIZE	INTEGER	The minimum size (in bytes) of the results returned by the procedure.
MAX_RESULT_SIZE	INTEGER	The maximum size (in bytes) of the results returned by the procedure.
AVG_RESULT_SIZE	INTEGER	The average size (in bytes) of the results returned by the procedure.
MIN_PARAMETER_SET_SIZE	INTEGER	The minimum size (in bytes) of the parameters passed as input to the procedure.
MAX_PARAMETER_SET_SIZE	INTEGER	The maximum size (in bytes) of the parameters passed as input to the procedure.
AVG_PARAMETER_SET_SIZE	INTEGER	The average size (in bytes) of the parameters passed as input to the procedure.
ABORTS	BIGINT	The number of times the procedure was aborted.
FAILURES	BIGINT	The number of times the procedure failed unexpectedly. (As opposed to user aborts or expected errors, such as constraint violations.)

PROCEDUREPROFILE — Returns a row for every stored procedure that has been executed on the cluster, summarized across the cluster.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the information was collected (in milliseconds).
PROCEDURE	STRING	The class name of the stored procedure.
WEIGHTED_PERC	BIGINT	A weighted average of the execution time for this stored procedure compared to all stored procedure invocations.
INVOCATIONS	BIGINT	The total number of invocations of this procedure.
AVG	BIGINT	The average length of time (in nanoseconds) it took to execute the stored procedure.
MIN	BIGINT	The minimum length of time (in nanoseconds) it took to execute the stored procedure.

Name	Datatype	Description
MAX	BIGINT	The maximum length of time (in nanoseconds) it took to execute the stored procedure.
ABORTS	BIGINT	The number of times the procedure was aborted.
FAILURES	BIGINT	The number of times the procedure failed unexpectedly. (As opposed to user aborts or expected errors, such as constraint violations.)

SNAPSHOTSTATUS — Returns a row for every snapshot file in the recent snapshots performed on the cluster.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the snapshot was initiated (in milliseconds).
HOST_ID	INTEGER	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
TABLE	STRING	The name of the database table whose data the file contains.
PATH	STRING	The directory path where the snapshot file resides.
FILENAME	STRING	The file name.
NONCE	STRING	The unique identifier for the snapshot.
TXNID	BIGINT	The transaction ID of the snapshot.
START_TIME	BIGINT	The timestamp when the snapshot began (in milliseconds).
END_TIME	BIGINT	The timestamp when the snapshot was completed (in milliseconds).
SIZE	BIGINT	The total size, in bytes, of the file.
DURATION	BIGINT	The length of time (in milliseconds) it took to complete the snapshot.
THROUGHPUT	FLOAT	The average number of bytes per second written to the file during the snapshot process.
RESULT	STRING	String value indicating whether the writing of the snapshot file was successful ("SUCCESS") or not ("FAILURE").

TABLE — Returns a row for every table, per partition. In other words, the number of tables, multiplied by the number of sites per host and the number of hosts.

Name	Datatype	Description
TIMESTAMP	BIGINT	The timestamp when the information was collected (in milliseconds).
HOST_ID	BIGINT	Numeric ID for the host node.
HOSTNAME	STRING	Server name of the host node.
SITE_ID	BIGINT	Numeric ID of the execution site on the host node.
PARTITION_ID	BIGINT	The numeric ID for the logical partition that this site represents. When using a K value greater than zero, there are multiple copies of each logical partition.

Name	Datatype	Description
TABLE_NAME	STRING	The name of the database table.
TABLE_TYPE	STRING	The type of the table. Values returned include "Persistent-Table" for normal data tables and views and "Streamed-Table" for export-only tables.
TUPLE_COUNT	BIGINT	The number of rows currently stored for this table in the current partition. For export-only tables, the cumulative total number of rows inserted into the table.
TUPLE_ALLOCATED_MEMORY	INTEGER	The total size of memory, in kilobytes, allocated for storing inline data associated with this table in this partition. The allocated memory can exceed the currently used memory (TUPLE_DATA_MEMORY). For export-only tables, this field identifies the amount of memory currently in use to queue export data (both in memory and as export overflow) prior to its being passed to the export client.
TUPLE_DATA_MEMORY	INTEGER	The total memory, in kilobytes, used for storing inline data associated with this table in this partition. The total memory used for storing data for this table is the combination of memory used for inline (tuple) and non-inline (string) data.
STRING_DATA_MEMORY	INTEGER	The total memory, in kilobytes, used for storing non-inline variable length data (VARCHAR and VARBINARY) associated with this table in this partition. The total memory used for storing data for this table is the combination of memory used for inline (tuple) and non-inline (string) data.

Examples

The following example uses @Statistics to gather information about the distribution of table rows within the cluster. The example uses the toString() method of VoltTable to display the results of the procedure call.

```
try {
    VoltTable[] results = client.callProcedure("@Statistics",
                                                "TABLE", 0).getResults();
    for (VoltTable t: results) { System.out.println(t.toString()); }
}
catch (Exception e) {
    e.printStackTrace();
}
```

The following example shows a procedure that collects and displays the number of transactions (i.e. stored procedures) during a given interval, by setting the delta-flag to a non-zero value. By calling this procedure iteratively (for example, every five minutes), it is possible to identify fluctuations in the database workload over time (as measured by the number of transactions processed).

```
void measureWorkload() {
    VoltTable[] results = null;
    String procName;
    int procCount = 0;
    int sysprocCount = 0;

    try { results = client.callProcedure("@Statistics",
        "INITIATOR",1).getResults(); }
    catch (Exception e) { e.printStackTrace(); }

    for (VoltTable t: results) {
        for (int r=0;r<t.getRowCount();r++) {
            VoltTableRow row = t.fetchRow(r);
            procName = row.getString("PROCEDURE_NAME");
            /* Count system procedures separately */
            if (procName.substring(0,1).compareTo("@") == 0)
                { sysprocCount += row.getLong("INVOCATIONS"); }
            else
                { procCount += row.getLong("INVOCATIONS"); }
        }
    }
    System.out.printf("System procedures: %d\n" +
        "User-defined procedures: %d\n",+
        sysprocCount,procCount);
}
```

@SystemCatalog

@SystemCatalog — Returns metadata about the database schema

Syntax

```
ClientResponse client.callProcedure("@SystemCatalog", String component)
```

Description

The @SystemCatalog system procedure returns information about the schema of the VoltDB database, depending upon the component keyword you specify. The following are the allowable values of *component*:

"TABLES"	Returns information about the tables in the database.
"COLUMNS"	Returns a list of columns for all of the tables in the database.
"INDEXINFO"	Returns information about the indexes in the database schema. Note that the procedure returns information for each column in the index. In other words, if an index is composed of three columns, the result set will include three separate entries for the index, one for each column.
"PRIMARYKEYS"	Returns information about the primary keys in the database schema. Note that the procedure returns information for each column in the primary key. If an primary key is composed of three columns, the result set will include three separate entries.
"PROCEDURES"	Returns information about the stored procedures defined in the application catalog, including system procedures.
"PROCEDURECOLUMNS"	Returns information about the arguments to the stored procedures.

Return Values

Returns a different VoltTable for each component. The layout of the VoltTables is designed to match the corresponding JDBC data structures. Columns are provided for all JDBC properties, but where VoltDB has no corresponding element the column is unused and a null value is returned.

For the TABLES component, the VoltTable has the following columns:

Name	Datatype	Description
TABLE_CAT	STRING	Unused.
TABLE_SCHEM	STRING	Unused.
TABLE_NAME	STRING	The name of the database table.
TABLE_TYPE	STRING	Specifies whether the table is a data table ("TABLE"), a materialized view ("VIEW"), or an export-only table ('EXPORT').
REMARKS	STRING	Unused.
TYPE_CAT	STRING	Unused.

Name	Datatype	Description
TYPE_SCHEM	STRING	Unused.
TYPE_NAME	STRING	Unused.
SELF_REFERENCING_COL_NAME	STRING	Unused.
REF_GENERATION	STRING	Unused.

For the COLUMNS component, the VoltTable has the following columns:

Name	Datatype	Description
TABLE_CAT	STRING	Unused.
TABLE_SCHEM	STRING	Unused.
TABLE_NAME	STRING	The name of the database table the column belongs to.
COLUMN_NAME	STRING	The name of the column.
DATA_TYPE	INTEGER	An enumerated value specifying the corresponding Java SQL datatype of the column.
TYPE_NAME	STRING	A string value specifying the datatype of the column.
COLUMN_SIZE	INTEGER	The length of the column in bits, characters, or digits, depending on the datatype.
BUFFER_LENGTH	INTEGER	Unused.
DECIMAL_DIGITS	INTEGER	The number of fractional digits in a DECIMAL datatype column. (Null for all other datatypes.)
NUM_PREC_RADIX	INTEGER	Specifies the radix, or numeric base, for calculating the column size. A radix of 2 indicates the column size is measured in bits while a radix of 10 indicates a measurement in bytes or digits.
NULLABLE	INTEGER	Indicates whether the column value can be null (1) or not (0).
REMARKS	STRING	Contains the string "PARTITION_COLUMN" if the column is the partitioning key for a partitioned table. Otherwise null.
COLUMN_DEF	STRING	The default value for the column.
SQL_DATA_TYPE	INTEGER	Unused.
SQL_DATETIME_SUB	INTEGER	Unused.
CHAR_OCTET_LENGTH	INTEGER	For variable length columns (VARCHAR and VARBINARY), the maximum length of the column. Null for all other datatypes.
ORDINAL_POSITION	INTEGER	An index specifying the position of the column in the list of columns for the table, starting at 1.
IS_NULLABLE	STRING	Specifies whether the column can contain a null value ("YES") or not ("NO").
SCOPE_CATALOG	STRING	Unused.
SCOPE_SCHEMA	STRING	Unused.
SCOPE_TABLE	STRING	Unused.

Name	Datatype	Description
SOURCE_DATE_TYPE	SMALLINT	Unused.
IS_AUTOINCREMENT	STRING	Specifies whether the column is auto-incrementing or not. (Always returns "NO").

For the INDEXINFO component, the VoltTable has the following columns:

Name	Datatype	Description
TABLE_CAT	STRING	Unused.
TABLE_SCHEM	STRING	Unused.
TABLE_NAME	STRING	The name of the database table the index applies to.
NON_UNIQUE	TINYINT	Value specifying whether the index is unique (0) or not (1).
INDEX_QUALIFIER	STRING	Unused.
INDEX_NAME	STRING	The name of the index that includes the current column.
TYPE	SMALLINT	An enumerated value indicating the type of index as either a hash (2) or other type (3) of index.
ORDINAL_POSITION	SMALLINT	An index specifying the position of the column in the index, starting at 1.
COLUMN_NAME	STRING	The name of the column.
ASC_OR_DESC	STRING	A string value specifying the sort order of the index. Possible values are "A" for ascending or null for unsorted indexes.
CARDINALITY	INTEGER	Unused.
PAGES	INTEGER	Unused.
FILTER_CONDITION	STRING	Unused.

For the PRIMARYKEYS component, the VoltTable has the following columns:

Name	Datatype	Description
TABLE_CAT	STRING	Unused.
TABLE_SCHEM	STRING	Unused.
TABLE_NAME	STRING	The name of the database table.
COLUMN_NAME	STRING	The name of the column in the primary key.
KEY_SEQ	SMALLINT	An index specifying the position of the column in the primary key, starting at 1.
PK_NAME	STRING	The name of the primary key.

For the PROCEDURES component, the VoltTable has the following columns:

Name	Datatype	Description
PROCEDURE_CAT	STRING	Unused.
PROCEDURE_SCHEM	STRING	Unused.
PROCEDURE_NAME	STRING	The name of the stored procedure.
RESERVED1	STRING	Unused.

Name	Datatype	Description
RESERVED2	STRING	Unused.
RESERVED3	STRING	Unused.
REMARKS	STRING	Unused.
PROCEDURE_TYPE	SMALLINT	An enumerated value that specifies the type of procedure. Always returns zero (0), indicating "unknown".
SPECIFIC_NAME	STRING	Same as PROCEDURE_NAME.

For the PROCEDURECOLUMNS component, the VoltTable has the following columns:

Name	Datatype	Description
PROCEDURE_CAT	STRING	Unused.
PROCEDURE_SCHEM	STRING	Unused.
PROCEDURE_NAME	STRING	The name of the stored procedure.
COLUMN_NAME	STRING	The name of the procedure parameter.
COLUMN_TYPE	SMALLINT	An enumerated value specifying the parameter type. Always returns 1, corresponding to procedureColumnIn.
DATA_TYPE	INTEGER	An enumerated value specifying the corresponding Java SQL datatype of the column.
TYPE_NAME	STRING	A string value specifying the datatype of the parameter.
PRECISION	INTEGER	The length of the parameter in bits, characters, or digits, depending on the datatype.
LENGTH	INTEGER	The length of the parameter in bytes. For variable length datatypes (VARCHAR and VARBINARY), this value specifies the maximum possible length.
SCALE	SMALLINT	The number of fractional digits in a DECIMAL datatype parameter. (Null for all other datatypes.)
RADIX	SMALLINT	Specifies the radix, or numeric base, for calculating the precision. A radix of 2 indicates the precision is measured in bits while a radix of 10 indicates a measurement in bytes or digits.
NULLABLE	SMALLINT	Unused.
REMARKS	STRING	If this column contains the string "PARTITION_PARAMETER", the parameter is the partitioning key for a single-partitioned procedure. If the column contains the string "ARRAY_PARAMETER" the parameter is a native Java array. Otherwise this column is null.
COLUMN_DEF	STRING	Unused.
SQL_DATA_TYPE	INTEGER	Unused.
SQL_DATETIME_SUB	INTEGER	Unused.
CHAR_OCTET_LENGTH	INTEGER	For variable length columns (VARCHAR and VARBINARY), the maximum length of the column. Null for all other datatypes.
ORDINAL_POSITION	INTEGER	An index specifying the position in the parameter list for the procedure, starting at 1.

Name	Datatype	Description
IS_NULLABLE	STRING	Unused.
SPECIFIC_NAME	STRING	Same as COLUMN_NAME

Example

The following example uses @SystemCatalog to display information about the tables in the database schema.

```
VoltTable[] results = null;
try {
    results = client.callProcedure("@SystemCatalog",
        "TABLES").getResults();
    System.out.println("Information about the database schema:");
    for (VoltTable node : results) System.out.println(node.toString());
}
catch (Exception e) {
    e.printStackTrace();
}
```

@SystemInformation

@SystemInformation — Returns configuration information about VoltDB and the individual nodes of the database cluster

Syntax

```
ClientResponse client.callProcedure("@SystemInformation")

ClientResponse client.callProcedure("@SystemInformation", String component)
```

Description

The @SystemInformation system procedure returns information about the configuration of the VoltDB database or the individual nodes of the database cluster, depending upon the component keyword you specify. The following are the allowable values of *component*:

"DEPLOYMENT"	Returns information about the configuration of the database. In particular, this keyword returns information about the various features and settings enabled through the deployment file, such as export, snapshots, K-safety, and so on. These properties are returned in a single VoltTable of name/value pairs.
"OVERVIEW"	Returns information about the individual servers in the database cluster, including the host name, the IP address, the version of VoltDB running on the server, as well as the path to the catalog and deployment files in use.

If you do not specify a component, @SystemInformation returns the results of the OVERVIEW component (to provide compatibility with previous versions of the procedure).

Return Values

Returns one of two VoltTables depending upon which component is requested.

For the DEPLOYMENT component, the VoltTable has the columns specified in the following table.

Name	Datatype	Description
PROPERTY	STRING	The name of the deployment property being reported.
VALUE	STRING	The corresponding value of that property in the deployment file (either explicitly or by default).

For the OVERVIEW component, information is reported for each server in the cluster, so an additional column is provided identifying the host node.

Name	Datatype	Description
HOST_ID	INTEGER	A numeric identifier for the host node..
KEY	STRING	The name of the system attribute being reported.
VALUE	STRING	The corresponding value of that attribute for the specified host.

Example

The following example uses `@SystemInformation` to display information about the nodes in the cluster and then about the database itself.

```
VoltTable[] results = null;
try {
    results = client.callProcedure("@SystemInformation",
                                   "OVERVIEW").getResults();
    System.out.println("Information about the database cluster:");
    for (VoltTable node : results) System.out.println(node.toString());

    results = client.callProcedure("@SystemInformation",
                                   "DEPLOYMENT").getResults();
    System.out.println("Information about the database deployment:");
    for (VoltTable node : results) System.out.println(node.toString());
}
catch (Exception e) {
    e.printStackTrace();
}
```

@UpdateApplicationCatalog

@UpdateApplicationCatalog — Reconfigures the database by replacing the application catalog currently in use.

Syntax

```
ClientResponse client.callProcedure("@UpdateApplicationCatalog", byte[] catalog, String de-  
ployment)
```

Description

The @UpdateApplicationCatalog system procedure lets you make modifications to a running database without having to shutdown and restart. @UpdateApplicationCatalog supports the following changes:

- Add, remove, or modify stored procedures
- Add, remove, or modify database tables and columns
- Add, remove, or modify indexes (except where new constraints are introduced)
- Add or remove views and export-only tables
- Modify the security permissions for the database
- Modify the settings for automated snapshots (whether they are enabled or not, their frequency, location, prefix, and number retained)

When modifying indexes, you can add, remove, or rename non-unique indexes, you can add or remove columns from a non-unique index, and you can rename, add columns to, or remove in its entirety a unique index. The only limitations are that you *cannot* add a unique index or remove a column from an existing unique index.

The arguments to the system procedure are a byte array containing the contents of the new catalog jar and a string containing the contents of the deployment file. That is, you pass the actual contents of the catalog and deployment files, using a byte array for the binary catalog and a string for the text deployment file.

The new catalog and the deployment file must not contain any changes other than the allowed modifications listed above. Currently, if there are any other changes from the original catalog and deployment file (such as changes to the export configuration or to the configuration of the cluster), the procedure returns an error indicating that an incompatible change has been found.

If you call @updateApplicationCatalog on a master database while database replication (DR) is active, the DR process automatically communicates any changes to the application catalog to the replica database to keep the two databases in sync. However, any changes to the deployment file apply to the master database only. To change the deployment settings on a replica database, you must stop and restart the replica (and database replication) using an updated deployment file.

To simplify the process of encoding the catalog contents, the Java client interface includes two helper methods (one synchronous and one asynchronous) to encode the files and issue the stored procedure request:

```
ClientResponse client.updateApplicationCatalog( File catalog-file, File deployment-file)
```

ClientResponse client.updateApplicationCatalog(clientCallback *callback*, File *catalog-file*, File *deployment-file*)

Example

The following example uses the @UpdateApplicationCatalog directly to update the current database catalog, using the catalog at project/newcatalog.jar and configuration file at project/production.xml.

```
String newcat = "project/newcatalog.jar";
String newdeploy = "project/production.xml";

try {
    File file = new File(newcat);
    FileInputStream fin = new FileInputStream(file);
    byte[] catalog = new byte[(int)file.length()];
    fin.read(catalog);
    fin.close();
    file = new File(newdeploy);
    fin = new FileInputStream(file);
    byte[] deploybytes = new byte[(int)file.length()];
    fin.read(deploybytes);
    fin.close();
    String deployment = new String(deploybytes, "UTF-8");
    client.callProcedure("@UpdateApplicationCatalog", catalog, deployment);
}
catch (Exception e) { e.printStackTrace(); }
```

The following example uses the synchronous helper method to perform the same operation.

```
String newcat = "project/newcatalog.jar";
String newdeploy = "project/production.xml";
try {
    client.updateApplicationCatalog(new File(newcat), new File(newdeploy));
}
catch (Exception e) { e.printStackTrace(); }
```

@UpdateLogging

@UpdateLogging — Changes the logging configuration for a running database.

Syntax

ClientResponse client.callProcedure("@UpdateLogging", String *configuration*)

Description

The @UpdateLogging system procedure lets you change the logging configuration for VoltDB. The second argument, *configuration*, is a text string containing the Log4J XML configuration definition.

Return Values

Returns one VoltTable with one row.

Name	Datatype	Description
STATUS	BIGINT	Always returns the value zero (0) indicating success.

Example

The following example shows one way to update the logging using the contents of an XML file (identified by the string *xmlfilename*) .

```
try {
    Scanner scan = new Scanner(new File(xmlfilename));
    scan.useDelimiter("\\Z");
    String content = scan.next();
    client.callProcedure("@UpdateLogging",content);
}
catch (Exception e) {
    e.printStackTrace();
}
```