

Version 1.0-alpha5 July 2009

Ed Hartnett Unidata Program Center

Copyright © 2006 University Corporation for Atmospheric Research Permission is granted to make and distribute verbatim copies of this manual provided that the copyright notice and these paragraphs are preserved on all copies. The software and any accompanying written materials are provided "as is" without warranty of any kind. UCAR expressly disclaims all warranties of any kind, either expressed or implied, including but not limited to the implied warranties of merchantability and fitness for a particular purpose. The Unidata Program Center is managed by the University Corporation for Atmospheric Research and sponsored by the National Science Foundation. Any opinions, findings, conclusions, or recommendations expressed in this publication are those of the author(s) and do not necessarily reflect the views of the National Science Foundation. Mention of any commercial company or product in this document does not constitute an endorsement by the Unidata Program Center. Unidata does not authorize any use of information from this publication for advertising or publicity purposes.

Table of Contents

\mathbf{S}	umı	mary	1
D	owı	nloading and Installing libcf	3
1	\mathbf{T}	he cfcheck Utility	5
2	${f F}$	iles	7
	2.1	Mark a File as Conforming to CF Conventions	. 7
	2.2	Determine if a File Claims to Conform to CF Conventions	
	2.3	Add description to the data with nccf_def_file	
	2.4	Read the description of the data with nccf_inq_file	
	2.5	Append to a History Attribute	10
3	\mathbf{V}	fariables	11
	3.1	Add description to a variable with nccf_def_var	11
	3.2	Read variable description with nccf_inq_var	
	3.3	Define missing data values for a variable with nccf_def_var_missi	
	3.4	Learn about missing data settings with nccf_inq_var_missing	
	3.5	Add CF-Recommended Metadata to a File or Variable with	
	3.6	Read variable description with nccf_inq_notes	14
	3.7	Define a coordinate variable and dimension for latitude with nccf_def_latitude	15
	3.8	Learn about a latitude coordinate variable and dimension with	10
	3. 0	Learn about a latitude coordinate variable and dimension with	16
	3.9	Define a coordinate variable and dimension for longitude with	
		9	17
	3.10	Learn about a longitude coordinate variable and dimension wit	h
			17
	3.11	Define a coordinate variable and dimension for level with	
	0.10	nccf_def_lvl	
	3.12 3.13	Learn about a level coordinate variable and dimension with	19
	0.10	Define a coordinate variable and dimension for level with nccf def lyl	20
	3.14		_
	3.15		_0
		nccf_def_time	21
	3.16		22
	3.17	Define atmosphere sigma coordinate	23
	3.18	1 0	
	3.19	• 0	
	3.20	Inquire about atmosphere sigma coordinate	24

	3.21	The formula_terms attribute for atmosphere hybrid height 25
	3.22	Inquire about hybrid height coordinate
	3.23	Define atmosphere sleve coordinate
	3.24	Inquire About Sleve Coordinate
	3.25	Define Ocean Sigma Coordinate
	3.26	Inquire About Ocean Sigma Coordinate
	3.27	
	3.28	Inquire About Ocean S Coordinate
	3.29	Define Ocean Sigma Z Coordinate
	3.30	Inquire About Ocean Sigma Z Coordinate
	3.31	Define Ocean Double Sigma Coordinate
	3.32	Inquire About Ocean Double Sigma Coordinate 33
	3.33	Get a geographic subset of the data
4	\mathbf{C}	oordinate Systems
	4.1	Label the axis type of a coordinate var with nccf_def_axis_type
	4.2	Find out the axis type of a coordinate var with nccf_inq_axis_type
	4.3	Define a coordinate system with nccf_def_coord_system 35
	4.4	Find out about a coordinate system with nccf_inq_coord_system
	4.5	Assign a coordinate system to a var with nccf_assign_coord_system
	4.6	Define a coordinate transform with nccf_def_transform 36
	4.7	Find out about a coordinate transform with nccf_inq_transform
		37
	4.8	Assign a coordinate transform to a coordinate system with
		$nccf_assign_transform$
Ir	nde	x

Summary 1

Summary

The CF conventions for climate and forecast metadata are designed to promote the processing and sharing of files created with the netCDF API.

This library, libcf, makes it easier to create and work with data files which conform to the CF conventions.

The functions of the CF library are intended to be interspersed with netCDF library calls. That is, the programmer will open or create a netCDF file with the netCDF API, and then add or read metadata with libcf library functions, then continue to working with the netCDF API to read and write data.

By using libcf, a data producer can produce files that conform to the CF standards, without having to write netCDF code to create and decode all the attributes that the CF convention uses to store meta-data. A data consumer can use libcf to read any file which conforms to the CF conventions; the file does not need to be created with libcf to be read by libcf.

Fortran-77 wrapper functions provide a Fortran 77 API, just as is done with netCDF itself. A Fortran 90 API is planned, but not yet begun.

For more information about the CF Conventions, see the CF Metadata web site at http://www.cgd.ucar.edu/cms/eaton/cf-metadata/CF-1.0.html.

Downloading and Installing libcf

Currently, and for some time to come, libcf is in alpha release. The code is tested, but not extensively. The API may be extended, and possibly changed, in each release.

You must have either netCDF-3 (or netCDF-4) installed. And reasonably recent version of netCDF should work. libef is tested with netCDF 3.6.2-beta4.

Get the latest version of the libcf tarball at the libcf ftp site: ftp://ftp.unidata.ucar.edu/pub/libcf Unpack the tarball, and run:

./configure --with-netcdf=/my/netcdf --prefix=/my/libcf && make check install > output

Where /my/netcdf is the root install directory of the netCDF library you want to use, and /my/libcf is the root directory where you want libcf installed. (They may be the same directory.)

If you wish to use netCDF-4, you must also have HDF5 and libz, the compression library, installed. In this case, configure libcf like this:

./configure --with-netcdf=/s/n4_new1/install --enable-netcdf-4 --with-hdf5=/home/ed/lo

If the build does not work for you, please email libef support: support-libef@unidata.ucar.edu. Please send the *complete* output of the configure and build output, in ASCII (the output.txt file produced by the above build commands), and the file config.log, which is generated by the configure script.

1 The cfcheck Utility

The cfchck utility will chck a file to see if it contains valid CF metadata. Messages about the file are printed to stdout.

Chapter 2: Files 7

2 Files

2.1 Mark a File as Conforming to CF Conventions

Mark the file as following CF-1.0 conventions.

This functions is called automatically by nccf_def_file, so need not be called by the user if nccf_def_file is being called.

Usage

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

2.2 Determine if a File Claims to Conform to CF Conventions

Determine if the file claims to follow CF-1.0 conventions. This function only checks the global "Conventions" attribute. It does not look at file metadata to ensure that this is a well-formed CF file. It only tells whether the file claims to be a CF file.

Usage

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

2.3 Add description to the data with nccf_def_file

Add some or all of the CF recommended text attributes to a file. Any parameters which are set to NULL will be ignored.

Usage

ncid The ncid of the file.

title If non-NULL, this text string will be written as the CF-recommended "title" attribute.

history If non-NULL, this text string will be written as the CF-recommended "history" attribute.

institution

If non-NULL, this text string will be written as the CF-recommended "institution" attribute.

source If non-NULL, this text string will be written as the CF-recommended "source" attribute.

comment If non-NULL, this text string will be written as the CF-recommended "comment" attribute.

references

If non-NULL, this text string will be written as the CF-recommended "references" attribute.

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

2.4 Read the description of the data with nccf_inq_file

Read any existing CF recommended text attributes from the file.

Recall that in C, strlens do not include the null terminator. To get the lengths before the strings (in order to allocated) pass NULL for any or all strings and the lengths will be returned. Then call the function again after allocating memory.

The CF version is guaranteed to be less than NC_MAX_NAME.

Any of these pointer arguments may be NULL, in which case it will be ignored.

Usage

ncid The ncid of the file.

Chapter 2: Files 9

title_lenp

Pointer to size_t which, if not NULL, will get the length of the title attribute.

Pointer to char array which, if not NULL, will get the title string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

history_lenp

Pointer to size_t which, if not NULL, will get the length of the history attribute.

history Pointer to char array which, if not NULL, will get the history string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

institution_lenp

Pointer to size_t which, if not NULL, will get the length of the institution attribute.

institution

Pointer to char array which, if not NULL, will get the institution string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

source_lenp

Pointer to size_t which, if not NULL, will get the length of the source attribute.

Pointer to char array which, if not NULL, will get the source string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

comment_lenp

Pointer to size_t which, if not NULL, will get the length of the comment attribute.

comment Pointer to char array which, if not NULL, will get the comment string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

references_lenp

Pointer to size_t which, if not NULL, will get the length of the references attribute.

references

Pointer to char array which, if not NULL, will get the references string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

2.5 Append to a History Attribute

This function appends a time-stamped history string to the history attribute, creating the attribute if it doesn't already exist.

Usage

```
int nccf_add_history(int ncid, const char *history);
```

ncid The ncid of the file.

history The string to append to the history attribute.

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

3 Variables

3.1 Add description to a variable with nccf_def_var

Usage

ncid The ncid of the file.

varid The varid of the netCDF variable being described.

units If non-NULL, this text string will be written as the CF-recommended "units" attribute.

long_name

If non-NULL, this text string will be written as the CF-recommended "long_name" attribute.

standard_name

If non-NULL, this text string will be written as the CF-recommended "standard_name" attribute.

ncoord_vars

Number of coordinate variables for this variable.

coord_varids

The variable IDs of the coordinate variables for this variable.

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

3.2 Read variable description with nccf_inq_var

Read any existing CF recommended text attributes from a variable.

Usage

ncid The ncid of the file.

varid The varid of the netCDF variable.

units_lenp

Pointer to size_t which, if not NULL, will get the length of the units attribute.

units Pointer to char array which, if not NULL, will get the long_name string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

long_name_lenp

Pointer to size_t which, if not NULL, will get the length of the long_name attribute.

long_name

Pointer to char array which, if not NULL, will get the long_name string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

standard_name_lenp

Pointer to size_t which, if not NULL, will get the length of the standard_name attribute.

standard_name

Pointer to char array which, if not NULL, will get the standard_name string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

ncoord_vars

Pointer to an integer, which, if non-NULL, will get the number of coordinate variables identified in the "coordinates" attribute.

coord_varids

Pointer to an array of integer, which, if non-NULL, will be filled with the variable IDs of the variables listed int he "coordinates" attribute.

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

3.3 Define missing data values for a variable with nccf_def_var_missing

nccf_def_notes

This function sets the "fill_value", "valid_min", and "valid_max" attributes.

Usage

ncid The ncid of the file.

varid The varid of the netCDF variable being described.

fill_valuep

If non-NULL, this will point to a value of the same type as this varid, which will be used as the fill_value for the data.

valid_minp

If non-NULL, this will point to a value of the same type as this varid, which will be written as the "valid_min" attribute. If this parameter is non-NULL, valid_max must also be provided.

valid_maxp

If non-NULL, this will point to a value of the same type as this varid, which will be written as the "valid_max" attribute. If this parameter is non-NULL, valid_min must also be provided.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.4 Learn about missing data settings with nccf_inq_var_missing

Get attributes which define missing data information. If the attributes are not there, then provide the valid data anyway, based on netCDF defaults.

Usage

ncid The ncid of the file.

varid The varid of the netCDF variable.

fill_valuep

If this is not NULL, the fill value of the variable will be written at this address by nccf_inq_var_missing. If the fill value was not defined for the variable, the netCDF default value will be used.

valid_minp

If this is not NULL, the valid_min value of the variable will be written at this address by nccf_inq_var_missing. If the valid_min was not defined for the variable, the netCDF default value will be used.

valid_maxp

If this is not NULL, the valid_max value of the variable will be written at this address by nccf_inq_var_missing. If the valid_max value was not defined for the variable, the netCDF default value will be used.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.5 Add CF-Recommended Metadata to a File or Variable with

nccf_def_notes

This functions writes up to four text attributes for either a variable, or an entire file. These text attributes, "institution," "source," "comment," and "references" are recommended by the CF Metadata Convention.

Usage

ncid The ncid of the file.

varid The varid of the netCDF variable being described. Use NC_GLOBAL if you wish these attributes to apply to the entire file.

institution

If non-NULL, this text string will be written as the CF-recommended "institution" attribute.

source If non-NULL, this text string will be written as the CF-recommended "source" attribute

comment If non-NULL, this text string will be written as the CF-recommended "comment" attribute.

references

If non-NULL, this text string will be written as the CF-recommended "references" attribute.

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

3.6 Read variable description with nccf_inq_notes

Read any existing CF recommended text attributes from a variable.

Usage

ncid The ncid of the file.

varid The varid of the netCDF variable.

institution_lenp

Pointer to size_t which, if not NULL, will get the length of the institution attribute.

institution

Pointer to char array which, if not NULL, will get the institution string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

source_lenp

Pointer to size_t which, if not NULL, will get the length of the source attribute.

Pointer to char array which, if not NULL, will get the source string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

comment_lenp

Pointer to size_t which, if not NULL, will get the length of the comment attribute.

comment Pointer to char array which, if not NULL, will get the comment string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

references_lenp

Pointer to size_t which, if not NULL, will get the length of the references attribute.

references

Pointer to char array which, if not NULL, will get the references string. Memory must be allocated before this function is called. Call this function with a NULL for this parameter to get the size first.

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

3.7 Define a coordinate variable and dimension for latitude with nccf_def_latitude

Define a coordinate variable and dimension with all the CF recommended attribute accessories for latitude.

Usage

ncid The ncid of the file.

len The length of this coordinate dimension.

xtype The type of this coordinate variable.

formula_terms

If non-NULL, a string which will be written as the "formula_terms" attribute on the coordinate variable.

lat_dimidp

If non-NULL, nccf_def_latitude will write the dimension ID of the netCDF dimension for the latitude here.

lat_varidp

If non-NULL, nccf_def_latitude will write the variable ID of the netCDF coordinate variable for the latitude here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.8 Learn about a latitude coordinate variable and dimension with

nccf_ing_latitude

Inquire about a latitude dimension and coordinate variable.

Usage

ncid The ncid of the file.

lenp If non-NULL, the length of the latitude dimension will be written here by nccf_inq_latitude.

xtypep If non-NULL, the type of the coordinate variable will be written here.

ft_lenp If non-NULL, the length of the value of the "formula_terms" attribute will be written here by ft_lenp. If there is no "formula_terms" attribute, zero will be written.

lat_dimidp

If non-NULL, the dimid of the latitude dimension will be written here.

lat_varidp

If non-NULL, the varid of the latitude coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.9 Define a coordinate variable and dimension for longitude with nccf_def_longitude

Define a coordinate variable and dimension with all the CF recommended attribute accessories for longitude.

Usage

ncid The ncid of the file.

len The length of this coordinate dimension.

xtype The type of this coordinate variable.

formula_terms

If non-NULL, a string which will be written as the "formula_terms" attribute on the coordinate variable.

lon_dimidp

If non-NULL, nccf_def_longitude will write the dimension ID of the netCDF dimension for the longitude here.

lon_varidp

If non-NULL, nccf_def_longitude will write the variable ID of the netCDF coordinate variable for the longitude here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.10 Learn about a longitude coordinate variable and dimension with

nccf_inq_longitude

Inquire about a longitude dimension and coordinate variable.

Usage

ncid The ncid of the file.

lenp If non-NULL, the length of the longitude dimension will be written here by nccf_inq_longitude.

xtypep If non-NULL, the type of the coordinate variable will be written here.

ft_lenp If non-NULL, the length of the value of the "formula_terms" attribute will be written here by ft_lenp. If there is no "formula_terms" attribute, zero will be written.

lon_dimidp

If non-NULL, the dimid of the longitude dimension will be written here.

lon_varidp

If non-NULL, the varid of the longitude coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.11 Define a coordinate variable and dimension for level with nccf_def_lvl

Define a coordinate variable and dimension with all the CF recommended attribute accessories for a vertical level.

Usage

ncid The ncid of the file.

name The name of the coordinate dimension and variable.

len The length of this coordinate dimension and variable.

xtype The type of this coordinate variable.

units If non-NULL, a string which will be written as the "units" attribute on the coordinate variable.

positive_up

Set to 0 and the attribute "positive" to "down". Set to any other value to get "up".

standard_name

If non-NULL, a string which will be written as the "standard_name" attribute on the coordinate variable.

long_name

If non-NULL, a string which will be written as the "long_name" attribute on the coordinate variable.

lon_dimidp

If non-NULL, nccf_def_lvl will write the dimension ID of the netCDF dimension for the level here.

lon_varidp

If non-NULL, nccf_def_lvl will write the variable ID of the netCDF coordinate variable for the level here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.12 Learn about a level coordinate variable and dimension with

nccf_inq_lvl

Inquire about a level dimension and coordinate variable.

Usage

ncid The ncid of the file.

name If non-NULL, the name of this vertical level dimension (and variable) will be written here.

lenp If non-NULL, the length of the level dimension will be written here by nccf_inq_lvl.

xtypep If non-NULL, the type of the coordinate variable will be written here.

ft_lenp If non-NULL, the length of the value of the "formula_terms" attribute will be written here by ft_lenp. If there is no "formula_terms" attribute, zero will be written.

positive_upp

If non-NULL, a one will be written here if the "positive" attribute of this coordinate variable is "up", a zero will be written if it is "down".

lvl_dimidp

If non-NULL, the dimid of the level dimension will be written here.

lvl_varidp

If non-NULL, the varid of the level coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.13 Define a coordinate variable and dimension for level with nccf_def_lvl

Define a unitless vertical coordinate variable and dimension from Apendix D of the CF Convention, with all the CF recommended attribute accessories for a vertical level.

Usage

ncid The ncid of the file.

lvl_type One of: CF_VERT_ATM_LN, CF_VERT_SIGMA, CF_VERT_HYBRID_SIGMA,

CF_VERT_HYBRID_HEIGHT, CF_VERT_SLEVE, CF_VERT_OCEAN_SIGMA,

CF_VERT_OCEAN_S, CF_VERT_OCEAN_SIGMA_Z, CF_VERT_OCEAN_DBL_SIGMA.

name The name of the coordinate dimension and variable.

xtype The type of this coordinate variable.

1en The length of this coordinate dimension and variable.

lvl_dimidp

If non-NULL, the function will write the dimension ID of the netCDF dimension for the level here.

llvl_varidp

If non-NULL, the function will write the variable ID of the netCDF coordinate variable for the level here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.14 Learn about a level coordinate variable and dimension with

nccf_inq_lvl

Inquire about a level dimension and coordinate variable.

Usage

ncid The ncid of the file.

name If non-NULL, the name of this vertical level dimension (and variable) will be

written here.

xtypep If non-NULL, the type of the coordinate variable will be written here.

lenp If non-NULL, the length of the level dimension will be written here.

lvl_typep

If non-NULL, the type of vertical dimension will be written here, one of CF_VERT_ATM_LN, CF_VERT_SIGMA, CF_VERT_HYBRID_SIGMA, CF_VERT_HYBRID_HEIGHT, CF_VERT_SLEVE, CF_VERT_OCEAN_SIGMA,

CF_VERT_OCEAN_S, CF_VERT_OCEAN_SIGMA_Z, CF_VERT_OCEAN_DBL_SIGMA.

lvl_dimidp

If non-NULL, the dimid of the level dimension will be written here.

lvl_varidp

If non-NULL, the varid of the level coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.15 Define a coordinate variable and dimension for time with nccf def time

Define a coordinate variable and dimension with all the CF recommended attribute accessories for time.

Usage

ncid The ncid of the file.

len The length of this coordinate dimension.

xtype The type of this coordinate variable.

formula_terms

If non-NULL, a string which will be written as the "formula_terms" attribute on the coordinate variable.

lon_dimidp

If non-NULL, nccf_def_time will write the dimension ID of the netCDF dimension for the time here.

lon_varidp

If non-NULL, nccf_def_time will write the variable ID of the netCDF coordinate variable for the time here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.16 Learn about a time coordinate variable and dimension with

 $nccf_inq_time$

Inquire about a time dimension and coordinate variable.

Usage

ncid The ncid of the file.

lenp If non-NULL, the length of the time dimension will be written here by nccf_inq_time.

xtypep If non-NULL, the type of the coordinate variable will be written here.

ft_lenp If non-NULL, the length of the value of the "formula_terms" attribute will be written here by ft_lenp. If there is no "formula_terms" attribute, zero will be written.

formula_terms

If non-NULL the value of the "formula_terms" attribute, if any, will be copied here.

time_dimidp

If non-NULL, the dimid of the time dimension will be written here.

time_varidp

If non-NULL, the varid of the time coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.17 Define atmosphere sigma coordinate.

Define formula terms attribute for atmosphere sigma coordinate variable.

Usage

ps_varid The variable ID of the ps variable.

ptop_varid

The variable ID of the ptop variable.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.18 Inquire about atmosphere sigma coordinate.

 $nccf_inq_time$

Inquire about atmosphere sigma coordinate.

Usage

ncid The ncid of the file.

name If non-NULL, this pointer gets the name of the coordinate variable and dimen-

sion.

xtypep If non-NULL, the type of the coordinate variable will be written here.

lenp If non-NULL, the length of the coordinate dimension will be written here.

ps_varidp

If non-NULL, the variable ID of the ps variable will be written here.

ptop_varidp

If non-NULL, the variable ID of the ptop variable will be written here.

lvl_dimidp

If non-NULL, the dimid of the coordinate dimension will be written here.

lvl_varidp

If non-NULL, the varid of the coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.19 Define atmosphere sigma coordinate.

Define formula terms attribute for atmosphere hybrid sigma coordinate variable.

Usage

```
int nccf_def_ft_hybrid_sigma(int ncid, int varid, int a_varid, int b_varid,
                                      int ps_varid, int p0_varid);
           The ncid of the file.
ncid
           The varid of the vertical coordinate variable.
varid
           The variable ID of the a variable.
a_varid
           The variable ID of the b variable.
b varid
          The variable ID of the ps variable.
ps_varid
ptop_varid
           The variable ID of the ptop variable.
```

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.20 Inquire about atmosphere sigma coordinate.

Inquire about atmosphere hybrid sigma coordinate.

Usage

lenp

```
int nccf_inq_lvl_hybrid_sigma(int ncid, char *name, nc_type *xtypep,
                                       size_t *lenp, int *a_varidp, int *b_varidp,
                                       int *ps_varidp, int *p0_varidp, int *lvl_dimidp,
                                       int *lvl_varidp);
           The ncid of the file.
ncid
           If non-NULL, this pointer gets the name of the coordinate variable and dimen-
name
           If non-NULL, the type of the coordinate variable will be written here.
xtypep
           If non-NULL, the length of the coordinate dimension will be written here.
```

If non-NULL, the variable ID of the a variable will be written here.

b_varidp If non-NULL, the variable ID of the b variable will be written here.

ps_varidp

If non-NULL, the variable ID of the ps variable will be written here.

ptop_varidp

If non-NULL, the variable ID of the ptop variable will be written here.

lvl_dimidp

If non-NULL, the dimid of the coordinate dimension will be written here.

lvl_varidp

If non-NULL, the varid of the coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.21 The formula_terms attribute for atmosphere hybrid height

Define formula terms attribute for atmosphere hybrid height coordinate variable

Usage

ncid The ncid of the file.

varid The varid of the vertical coordinate variable.

a_varid The variable ID of the a variable.

b_varid The variable ID of the b variable.

orog_varid

The variable ID of the orog variable.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.22 Inquire about hybrid height coordinate.

Inquire about the hybrid height coordinate.

Usage

ncid The ncid of the file.

name If non-NULL, this pointer gets the name of the coordinate variable and dimen-

sion.

xtypep If non-NULL, the type of the coordinate variable will be written here.

lenp If non-NULL, the length of the coordinate dimension will be written here.

a_varidp If non-NULL, the variable ID of the a variable will be written here.

b_varidp If non-NULL, the variable ID of the b variable will be written here.

orog_varidp

If non-NULL, the variable ID of the orog variable will be written here.

lvl_dimidp

If non-NULL, the dimid of the coordinate dimension will be written here.

lvl_varidp

If non-NULL, the varid of the coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.23 Define atmosphere sleve coordinate.

Define formula terms attribute for the atmosphere sleve coordinate variable.

Usage

ncid The ncid of the file.

varid The varid of the vertical coordinate variable.

a_varid The variable ID of the a variable.

b1 varid The variable ID of the b1 variable.

b2_varid The variable ID of the b2 variable.

ztop_varid

The variable ID of the ztop variable.

zsurf1_varid

The variable ID of the zsurf1 variable.

zsurf2_varid

The variable ID of the zsurf2 variable.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.24 Inquire About Sleve Coordinate.

Inquire about the sleve coordinate.

Usage

ncid The ncid of the file.

name If non-NULL, this pointer gets the name of the coordinate variable and dimen-

xtypep If non-NULL, the type of the coordinate variable will be written here.

lenp If non-NULL, the length of the coordinate dimension will be written here.

a_varidp If non-NULL, the variable ID of the a variable will be written here.

b1_varidp

If non-NULL, the variable ID of the b1 variable will be written here.

b2_varidp

If non-NULL, the variable ID of the b2 variable will be written here.

ztop_varidp

If non-NULL, the variable ID of the ztop variable will be written here.

zsurf1_varidp

If non-NULL, the variable ID of the zsurf1 variable will be written here.

zsurf2_varidp

If non-NULL, the variable ID of the zsurf2 variable will be written here.

lvl_dimidp

If non-NULL, the dimid of the coordinate dimension will be written here.

lvl_varidp

If non-NULL, the varid of the coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.25 Define Ocean Sigma Coordinate.

Define the formula terms attribute for the ocean sigma coordinate variable.

Usage

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.26 Inquire About Ocean Sigma Coordinate.

Inquire about the ocean sigma coordinate.

Usage

```
int nccf_inq_lvl_ocean_sigma(int ncid, char *name, nc_type *xtypep, size_t *lenp,
                                      int *eta_varidp, int *depth_varidp, int *lvl_dimidp,
                                      int *lvl_varidp);
           The ncid of the file.
ncid
           If non-NULL, this pointer gets the name of the coordinate variable and dimen-
name
           If non-NULL, the type of the coordinate variable will be written here.
xtypep
           If non-NULL, the length of the coordinate dimension will be written here.
lenp
eta_varidp
           If non-NULL, the variable ID of the eta variable will be written here.
lvl_dimidp
           If non-NULL, the dimid of the coordinate dimension will be written here.
lvl_varidp
```

If non-NULL, the varid of the coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.27 Define Ocean S Coordinate.

Define ocean s coordinate.

Usage

ncid The ncid of the file.

varid The varid of the vertical coordinate variable.

xtype The type of this coordinate variable.

len The length of this coordinate dimension.

eta_varid

The variable ID of the eta variable.

depth_varid

The variable ID of the depth variable.

a_varid The variable ID of the a variable.

b_varid The variable ID of the b variable.

depth_c_varid

The variable ID of the depth_c variable.

lvl_dimidp

If non-NULL, the dimension ID of the netCDF coordinate dimension will be written here.

lvl_varidp

If non-NULL, the variable ID of the netCDF coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.28 Inquire About Ocean S Coordinate.

nccf_inq_time

Inquire about the ocean s coordinate.

Usage

ncid The ncid of the file.

name If non-NULL, this pointer gets the name of the coordinate variable and dimen-

sion.

xtypep If non-NULL, the type of the coordinate variable will be written here.

lenp If non-NULL, the length of the coordinate dimension will be written here.

eta_varidp

If non-NULL, the variable ID of the eta variable will be written here.

depth_varidp

If non-NULL, the variable ID of the depth variable will be written here.

a_varidp If non-NULL, the variable ID of the a variable will be written here.

b_varidp If non-NULL, the variable ID of the b variable will be written here.

depth_c_varidp

If non-NULL, the variable ID of the depth_c variable will be written here.

lvl_dimidp

If non-NULL, the dimid of the coordinate dimension will be written here.

lvl_varidp

If non-NULL, the varid of the coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.29 Define Ocean Sigma Z Coordinate.

Define ocean sigma z coordinate.

Usage

ncid The ncid of the file.

varid The varid of the vertical coordinate variable.

xtype The type of this coordinate variable.

len The length of this coordinate dimension.

eta_varid

The variable ID of the eta variable.

depth_varid

The variable ID of the depth variable.

depth_c_varid

The variable ID of the depth_c variable.

nsigma_varid

The variable ID of the nsigma variable.

zlev_varid

The variable ID of the zlev variable.

lvl_dimidp

If non-NULL, the dimension ID of the netCDF coordinate dimension will be written here.

lvl_varidp

If non-NULL, the variable ID of the netCDF coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.30 Inquire About Ocean Sigma Z Coordinate.

Inquire about the ocean sigma z coordinate.

Usage

ncid The ncid of the file.

name If non-NULL, this pointer gets the name of the coordinate variable and dimension

xtypep If non-NULL, the type of the coordinate variable will be written here.

lenp If non-NULL, the length of the coordinate dimension will be written here.

eta_varidp

If non-NULL, the variable ID of the eta variable will be written here.

depth_varidp

If non-NULL, the variable ID of the depth variable will be written here.

```
depth_c_varidp
```

If non-NULL, the variable ID of the depth_c variable will be written here.

nsigma_varidp

If non-NULL, the variable ID of the nsigma variable will be written here.

zlev_varidp

If non-NULL, the variable ID of the zlev variable will be written here.

lvl_dimidp

If non-NULL, the dimid of the coordinate dimension will be written here.

lvl_varidp

If non-NULL, the varid of the coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.31 Define Ocean Double Sigma Coordinate.

Define ocean double sigma coordinate.

Usage

ncid The ncid of the file.

varid The varid of the vertical coordinate variable.

xtype The type of this coordinate variable.

len The length of this coordinate dimension.

depth_varid

The variable ID of the depth variable.

z1_varid The variable ID of the z1 variable.

z2_varid The variable ID of the z2 variable.

a_varid The variable ID of the a variable.

href_varid

The variable ID of the href variable.

k_c_varid

The variable ID of the k_c variable.

lvl_dimidp

If non-NULL, the dimension ID of the netCDF coordinate dimension will be written here.

lvl_varidp

If non-NULL, the variable ID of the netCDF coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.32 Inquire About Ocean Double Sigma Coordinate.

Inquire about the ocean double sigma coordinate.

Usage

ncid The ncid of the file.

name If non-NULL, this pointer gets the name of the coordinate variable and dimension

xtypep If non-NULL, the type of the coordinate variable will be written here.

lenp If non-NULL, the length of the coordinate dimension will be written here.

depth_varidp

If non-NULL, the variable ID of the depth variable will be written here.

z1_varidp

If non-NULL, the variable ID of the z1 variable will be written here.

z2_varidp

If non-NULL, the variable ID of the z2 variable will be written here.

a_varidp If non-NULL, the variable ID of the a variable will be written here.

href_varidp

If non-NULL, the variable ID of the href variable will be written here.

k_c_varidp

If non-NULL, the variable ID of the k_c variable will be written here.

lvl_dimidp

If non-NULL, the dimid of the coordinate dimension will be written here.

lvl_varidp

If non-NULL, the varid of the coordinate variable will be written here.

Return Codes

This function returns zero for success, or an error code for failure.

Example

3.33 Get a geographic subset of the data.

Get a geographic subset of the data.

Usage

int nccf_get_vara(int ncid, int varid, float *lat_bounds, int *nlat, float *lon_bou
int *nlon, int *lvl_index, int *nlvl, int rec, void *data);

ncid The ncid of the file.

varid The varid of the data variable from which the subset will be taken.

lat_bounds

A length two array, this holds the latitude start and stop values for the range of interest.

A pointer to an integer which will get the number of latitude values which fall within the range.

lon_bounds

A length two array, this holds the longitude start and stop values for the range of interest. (Wrapping around the dateline is not allowed!)

A pointer to an integer which will get the number of longitude values which fall within the range.

lvl_index

A zero-based index number for the verticle level of interest to the subsetter. (Ignored if data has no vertical axis).

timestep A zero-based index number for the timestep of interest to the subsetter. (Ignored if data has no time axis).

A pointer to which the data subset will be written. Memory must be allocated (and deallocated) by the user.

Return Codes

This function returns zero for success, or an error code for failure.

Example

4 Coordinate Systems

4.1 Label the axis type of a coordinate var with nccf_def_axis_type

Usage

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

4.2 Find out the axis type of a coordinate var with nccf_inq_axis_type

Usage

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

4.3 Define a coordinate system with nccf_def_coord_system

Usage

Define a coordinate system consisting of naxes axes, each axis represented by a coordinate varid in the axis_varids array. This create a new (scalar, NC_CHAR) var, whose varid is returned in system_varid.

ncid The ncid of the file.

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

4.4 Find out about a coordinate system with nccf_inq_coord_system

Usage

Find out about a coordinate system, it's name, number of axes, and the varid of each axis coordinate var.

ncid The ncid of the file.

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

4.5 Assign a coordinate system to a var with nccf_assign_coord_system

Usage

```
int
   nccf_assign_coord_system(int ncid, int varid, int system_varid);
Assign a coordinate system to a var. This adds an attribute to the var.
ncid   The ncid of the file.
```

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

4.6 Define a coordinate transform with nccf def transform

Usage

```
int
nccf_def_transform(int ncid, const char *name, const char *transform_type,
```

```
const char *transform_name, int *transform_varid);
```

Define a coordinate transform. This adds a (scalar, NC_CHAR) var, which contains some attributes. The varid of this new variable is returned in transform_varid.

ncid The ncid of the file.

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

4.7 Find out about a coordinate transform with nccf_inq_transform

Usage

Find out about a coordinate transform, it's name, and the contents of the transform_type and transform_name attributes. Pass NULL for any that you're not interested in. Pass NULL for transform_type and transform_name to get their lengths with type_len and name_len.

ncid The ncid of the file.

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

4.8 Assign a coordinate transform to a coordinate system with nccf_assign_transform

Usage

```
int
```

```
nccf_assign_transform(int ncid, int system_varid, int transform_varid);
```

Assign a coordinate transform to a coordinate system. This adds an attribute to the variable that holds the coordinate system attributes.

ncid The ncid of the file.

Return Codes

This function returns zero for success, or a netCDF error code for failure.

Example

Index 39

\mathbf{Index}

\mathbf{A}	\mathbf{S}
API, C	
API, F90 1	
API, Fortran	supported programming languages