Installation

Contents

Deployment Requirements	 2
Documentation	 2
conf Directory	 3
$conf/postgres-operator/pgo.yaml \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $	 3
conf/postgres-operator Directory	 3
Security	 3
Local pgo CLI Configuration	 4
Namespace Configuration	 4
pgo.yaml Configuration	4
Storage	 4
Storage Configuration Examples	 5
HostPath Example	 5
NFS Example	 5
Storage Class Example	 5
Container Resources	 5
Miscellaneous (Pgo)	 6
Storage Configuration Details	 6
Container Resources Details	 7
Overriding Storage Configuration Defaults	 7
Using Storage Configurations for Disaster Recovery	 7
Kubernetes RBAC	 7
Operator RBAC	 8
Making Security Changes	 10
API Security	 10
Upgrading the Operator	 10
Upgrading to Version 3.5.0 From Previous Versions	 11

itle: "Crunchy Data Postgres Operator"

ate:

raft: false

Latest Release: 4.0.0

The postgres-operator is a controller that runs within a Kubernetes cluster that provides a means to deploy and manage PostgreSQL clusters.

Use the postgres-operator to:

- deploy PostgreSQL containers including streaming replication clusters
- scale up PostgreSQL clusters with extra replicas
- add pgpool, pgbouncer, and metrics sidecars to PostgreSQL clusters
- apply SQL policies to PostgreSQL clusters
- assign metadata tags to PostgreSQL clusters
- $\bullet\,$ maintain PostgreSQL users and passwords
- perform minor upgrades to PostgreSQL clusters
- load simple CSV and JSON files into PostgreSQL clusters
- perform database backups

Deployment Requirements

The Operator deploys on Kubernetes and OpenShift clusters. Some form of storage is required, NFS, HostPath, and Storage Classes are currently supported.

The Operator includes various components that get deployed to your Kubernetes cluster as shown in the following diagram and detailed in the Design.

Postgres Operator Architecture




Figure 1: Architecture

The Operator is developed and tested on CentOS and RHEL Linux platforms but is known to run on other Linux variants.

Documentation

The following documentation is provided:

- pgo CLI Syntax and Examples
- Installation
- Configuration
- pgo.yaml Configuration
- Security
- Design Overview
- Developing
- Upgrading the Operator
- Contributing

The operator is template-driven; this makes it simple to configure both the client and the operator.

conf Directory

The Operator is configured with a collection of files found in the *conf* directory. These configuration files are deployed to your Kubernetes cluster when the Operator is deployed. Changes made to any of these configuration files currently require a redeployment of the Operator on the Kubernetes cluster.

The server components of the Operator include Role Based Access Control resources which need to be created a single time by a Kubernetes cluster-admin user. See the Installation section for details on installing a Postgres Operator server.

The configuration files used by the Operator are found in 2 places: * the pgo-config ConfigMap in the namespace the Operator is running in * or, a copy of the configuration files are also included by default into the Operator container images themselves to support a very simplistic deployment of the Operator

If the pgo-config ConfigMap is not found by the Operator, it will use the configuration files that are included in the Operator container images.

The container included set of configuration files use the most basic setting values and the image versions of the Operator itself with the latest Crunchy Container image versions. The storage configurations are determined by using the default storage class on the system you are deploying the Operator into, the default storage class is one that is labeled as follows:

pgo-default-sc=true

If no storage class has that label, then the first storage class found on the system will be used. If no storage class is found on the system, the containers will not run and produce an error in the log.

conf/postgres-operator/pgo.yaml

The pgo.yaml file sets many different Operator configuration settings and is described in the [pgo.yaml configuration]({{< ref "pgo-yaml-configuration.md" >}}) documentation section.

The pqo.yaml file is deployed along with the other Operator configuration files when you run:

make deployoperator

conf/postgres-operator Directory

Files within the *conf/postgres-operator* directory contain various templates that are used by the Operator when creating Kubernetes resources. In an advanced Operator deployment, administrators can modify these templates to add their own custom meta-data or make other changes to influence the Resources that get created on your Kubernetes cluster by the Operator.

Files within this directory are used specifically when creating PostgreSQL Cluster resources. Sidecar components such as pgBouncer and pgPool II templates are also located within this directory.

As with the other Operator templates, administrators can make custom changes to this set of templates to add custom features or metadata into the Resources created by the Operator.

Security

Setting up pgo users and general security configuration is described in the Security section of this documentation.

Local pgo CLI Configuration

You can specify the default namespace you want to use by setting the PGO_NAMESPACE environment variable locally on the host the pgo CLI command is running.

```
export PGO_NAMESPACE=pgouser1
```

When that variable is set, each command you issue with pgo will use that namespace unless you over-ride it using the -namespace command line flag.

pgo show cluster foo --namespace=pgouser2

Namespace Configuration

The Design Design section of this documentation talks further about the use of namespaces within the Operator and configuring different deployment models of the Operator.

pgo.yaml Configuration

Setting

The pgo.yaml file contains many different configuration settings as described in this section of the documentation.

The pgo.yaml file is broken into major sections as described below: ## Cluster

Definition

2 0
if set to true will enable Basic Authentication
newly created primary deployments will specify this node label if specified, unless you override it using the –
newly created replica deployments will specify this node label if specified, unless you override it using the –newly created replica deployments will specify this node label if specified, unless you override it using the
newly created containers will be based on this image prefix (e.g. crunchydata), update this if you require a cr
newly created containers will be based on this image version (e.g. centos7-11.2-2.4.0-rc2-1), unless you overries
the PostgreSQL port to use for new containers (e.g. 5432)
postgresql.conf log_statement value (required field)
$postgresql.conf \ log_min_duration_statement \ value \ (required \ field)$
the PostgreSQL normal user name
the PostgreSQL normal user database
the number of cluster replicas to create for newly created clusters, typically users will scale up replicas on the
the password to use for pgmonitor metrics collection if you specify –metrics when creating a PG cluster
boolean, if set to true will cause each new cluster to include crunchy-collect as a sidecar container for metrics
boolean, if set to true will cause each new cluster to include crunchy-pgbadger as a sidecar container for stat
optional, list of policies to apply to a newly created cluster, comma separated, must be valid policies in the c
optional, if set, will set the VALID UNTIL date on passwords to this many days in the future when creating
optional, if set, will determine the password length used when creating passwords, defaults to 8
optional, if set, will determine the service type used when creating primary or replica services, defaults to Cl
optional, if set, will cause clusters to have the pgbackrest volume PVC provisioned during cluster creation
currently required to be port 2022
optional, if set, will cause clusters to be checked for auto failover in the event of a non-Ready status

Storage

AutofailReplaceReplica

Setting	Definition
PrimaryStorage	required the value of the storage configuration to use for the primary PostgreSOL deployment

optional, default is false, if set, will determine whether a replica is created as part of a failover to replace the

Setting	Definition
BackupStorage	required, the value of the storage configuration to use for backups, including the storage for pgbackrest rep
ReplicaStorage	required, the value of the storage configuration to use for the replica PostgreSQL deployments
ReplicaStorage	required, the value of the storage configuration to use for the replica PostgreSQL deployments
BackrestStorage	required, the value of the storage configuration to use for the pgbackrest shared repository deployment cre
StorageClass	for a dynamic storage type, you can specify the storage class used for storage provisioning(e.g. standard, g
AccessMode	the access mode for new PVCs (e.g. ReadWriteMany, ReadWriteOnce, ReadOnlyMany). See below for des
Size	the size to use when creating new PVCs (e.g. 100M, 1Gi)
${\bf Storage 1. Storage Type}$	supported values are either dynamic, create, if not supplied, create is used
Fsgroup	optional, if set, will cause a SecurityContext and fsGroup attributes to be added to generated Pod and De
${\bf Supplemental Groups}$	optional, if set, will cause a Security Context to be added to generated Pod and Deployment definitions
MatchLabels	optional, if set, will cause the PVC to add a matchlabels selector in order to match a PV, only useful when

Storage Configuration Examples

In pgo.yaml, you will need to configure your storage configurations depending on which storage you are wanting to use for Operator provisioning of Persistent Volume Claims. The examples below are provided as a sample. In all the examples you are free to change the Size to meet your requirements of Persistent Volume Claim size.

HostPath Example

HostPath is provided for simple testing and use cases where you only intend to run on a single Linux host for your Kubernetes cluster.

hostpathstorage:

AccessMode: ReadWriteMany

Size: 1G

StorageType: create

NFS Example

In the following NFS example, notice that the Supplemental Groups setting is set, this can be whatever GID you have your NFS mount set to, typically we set this nfsnobody as below. NFS file systems offer a ReadWriteMany access mode.

nfsstorage:

AccessMode: ReadWriteMany

Size: 1G

StorageType: create

SupplementalGroups: 65534

Storage Class Example

In the following example, the important attribute to set for a typical Storage Class is the Fsgroup setting. This value is almost always set to 26 which represents the Postgres user ID that the Crunchy Postgres container runs as. Most Storage Class providers offer ReadWriteOnce access modes, but refer to your provider documentation for other access modes it might support.

storageos:

AccessMode: ReadWriteOnce

Size: 1G

StorageType: dynamic StorageClass: fast

Fsgroup: 26

Container Resources

Setting	Definition
DefaultContainerResource	optional, the value of the container resources configuration to use for all database containers, if not set, no re-
${\bf Default Load Resource}$	optional, the value of the container resources configuration to use for pgo-load containers, if not set, no resources
${\bf DefaultLspvcResource}$	optional, the value of the container resources configuration to use for pgo-lspvc containers, if not set, no reso
${\bf DefaultRmdataRe source}$	optional, the value of the container resources configuration to use for pgo-rmdata containers, if not set, no re
${\bf Default Backup Resource}$	optional, the value of the container resources configuration to use for crunchy-backup containers, if not set, n
${\bf DefaultPgbouncerResource}$	optional, the value of the container resources configuration to use for crunchy-pgbouncer containers, if not se
${\bf DefaultPgpoolResource}$	optional, the value of the container resources configuration to use for crunchy-pgpool containers, if not set, n
RequestsMemory	request size of memory in bytes
RequestsCPU	request size of CPU cores
LimitsMemory	request size of memory in bytes
LimitsCPU	request size of CPU cores

Miscellaneous (Pgo)

Setting	Definition
PreferredFailoverNode	optional, a label selector (e.g. hosttype=offsite) that if set, will be used to pick the failover target which is runnin
${\bf COImage Prefix}$	image tag prefix to use for the Operator containers
COImageTag	image tag to use for the Operator containers
Audit	boolean, if set to true will cause each a piserver call to be logged with an audit marking

Storage Configuration Details

You can define n-number of Storage configurations within the pgo.yaml file. Those Storage configurations follow these conventions -

- they must have lowercase name (e.g. storage1)
- they must be unique names (e.g. mydrstorage, faststorage, slowstorage)

These Storage configurations are referenced in the BackupStorage, ReplicaStorage, and PrimaryStorage configuration values. However, there are command line options in the pgo client that will let a user override these default global values to offer you the user a way to specify very targeted storage configurations when needed (e.g. disaster recovery storage for certain backups).

You can set the storage AccessMode values to the following:

- ReadWriteMany mounts the volume as read-write by many nodes
- ReadWriteOnce mounts the PVC as read-write by a single node
- ReadOnlyMany mounts the PVC as read-only by many nodes

These Storage configurations are validated when the *pgo-apiserver* starts, if a non-valid configuration is found, the apiserver will abort. These Storage values are only read at *apiserver* start time.

The following StorageType values are possible -

- dynamic this will allow for dynamic provisioning of storage using a StorageClass.
- create This setting allows for the creation of a new PVC for each PostgreSQL cluster using a naming convention of clustername. When set, the Size, AccessMode settings are used in constructing the new PVC.

The operator will create new PVCs using this naming convention: dbname where dbname is the database name you have specified. For example, if you run:

pgo create cluster example1 -n pgouser1

It will result in a PVC being created named example 1 and in the case of a backup job, the pvc is named example 1-backup

Note, when Storage Type is *create*, you can specify a storage configuration setting of *MatchLabels*, when set, this will cause a *selector* of key=value to be added into the PVC, this will let you target specific PV(s) to be matched for this cluster. Note, if a PV does not match the claim request, then the cluster will not start. Users that want to use this feature have to place labels on their PV resources as part of PG cluster creation before creating the PG cluster. For example, users would add a label like this to their PV before they create the PG cluster:

```
kubectl label pv somepv myzone=somezone -n pgouser1
```

If you do not specify *MatchLabels* in the storage configuration, then no match filter is added and any available PV will be used to satisfy the PVC request. This option does not apply to *dynamic* storage types.

Example PV creation scripts are provided that add labels to a set of PVs and can be used for testing: \$COROOT/pv/create-pv-nfs-labels.sh in that example, a label of crunchyzone=red is set on a set of PVs to test with.

The pgo.yaml includes a storage config named **nfsstoragered** that when used will demonstrate the label matching. This feature allows you to support n-number of NFS storage configurations and supports spreading a PG cluster across different NFS storage configurations.

Container Resources Details

In the *pgo.yaml* configuration file you have the option to configure a default container resources configuration that when set will add CPU and memory resource limits and requests values into each database container when the container is created.

You can also override the default value using the --resources-config command flag when creating a new cluster:

```
pgo create cluster testcluster --resources-config=large -n pgouser1
```

Note, if you try to allocate more resources than your host or Kube cluster has available then you will see your pods wait in a *Pending* status. The output from a kubectl describe pod command will show output like this in this event: Events:

Type	Reason	Age	From	Message
Warning	FailedScheduling	49s (x8 over 1m)	default-scheduler	No nodes are available that
match	all of the predic	cates: Insufficient	memory (1).	

Overriding Storage Configuration Defaults

```
pgo create cluster testcluster --storage-config=bigdisk -n pgouser1
```

That example will create a cluster and specify a storage configuration of bigdisk to be used for the primary database storage. The replica storage will default to the value of ReplicaStorage as specified in pgo.yaml.

```
pgo create cluster testcluster2 --storage-config=fastdisk --replica-storage-config=slowdisk -n pgouser1
```

That example will create a cluster and specify a storage configuration of *fastdisk* to be used for the primary database storage, while the replica storage will use the storage configuration *slowdisk*.

```
pgo backup testcluster --storage-config=offsitestorage -n pgouser1
```

That example will create a backup and use the *offsitestorage* storage configuration for persisting the backup.

Using Storage Configurations for Disaster Recovery

A simple mechanism for partial disaster recovery can be obtained by leveraging network storage, Kubernetes storage classes, and the storage configuration options within the Operator.

For example, if you define a Kubernetes storage class that refers to a storage backend that is running within your disaster recovery site, and then use that storage class as a storage configuration for your backups, you essentially have moved your backup files automatically to your disaster recovery site thanks to network storage.

Kubernetes RBAC

Install the requisite Operator RBAC resources, as a Kubernetes cluster admin user, by running a Makefile target:

make installrbac

This script creates the following RBAC resources on your Kubernetes cluster:

Setting	Definition
Custom Resource Definitions (crd.yaml)	pgbackups
	pgclusters
	pgpolicies
	pgreplicas
	pgtasks
	pgupgrades
Cluster Roles (cluster-roles.yaml)	pgopclusterrole
	pgopclusterrolecrd
Cluster Role Bindings (cluster-roles-bindings.yaml)	pgopclusterbinding
	pgopclusterbindingcrd
Service Account (service-accounts.yaml)	postgres-operator
	pgo-backrest
Roles (rbac.yaml)	pgo-role
	pgo-backrest-role
Role Bindings (rbac.yaml)	pgo-backrest-role-binding
	pgo-role-binding

Note that the cluster role bindings have a naming convention of pgopclusterbinding- $PGO_OPERATOR_NAMESPACE$ and to support The PGO_OPERATOR_NAMESPACE environment variable is added to make each cluster role binding name unique and to support more than a single Operator being deployed on the same Kube cluster.

Operator RBAC

The *conf/postgresql-operator/pgorole* file is read at start up time when the operator is deployed to the Kubernetes cluster. This file defines the Operator roles whereby Operator API users can be authorized.

The *conf/postgresql-operator/pgouser* file is read at start up time also and contains username, password, role, and namespace information as follows:

```
username:password:pgoadmin:
pgouser1:password:pgoadmin:pgouser1
pgouser2:password:pgoadmin:pgouser2
pgouser3:password:pgoadmin:pgouser1,pgouser2
readonlyuser:password:pgoreader:
```

The format of the prouser server file is:

```
<username>:<password>:<role>:<namespace,namespace>
```

The namespace is a comma separated list of namespaces that user has access to. If you do not specify a namespace, then all namespaces is assumed, meaning this user can access any namespace that the Operator is watching.

A user creates a *.pgouser* file in their \$HOME directory to identify themselves to the Operator. An entry in .pgouser will need to match entries in the *conf/postgresql-operator/pgouser* file. A sample *.pgouser* file contains the following:

```
username:password
```

The format of the .pgouser client file is:

```
<username>:<password>
```

The users prouser file can also be located at: /etc/pgo/pgouser or it can be found at a path specified by the PGOUSER environment variable.

If the user tries to access a name space that they are not configured for within the server side pgouser file then they will get an error message as follows:

```
Error: user [pgouser1] is not allowed access to namespace [pgouser2]
```

The following list shows the current complete list of possible pgo permissions that you can specify within the *pgorole* file when creating roles:

Permission	Description
ApplyPolicy	allow pgo apply
Cat	allow pgo cat
CreateBackup	allow pgo backup
${\bf Create Benchmark}$	allow pgo create benchmark
${\bf CreateCluster}$	allow pgo create cluster
${\bf CreateDump}$	allow pgo create pgdump
CreateFailover	allow pgo failover
${\bf Create Pg bouncer}$	allow pgo create pgbouncer
${\bf Create Pgpool}$	allow pgo create pgpool
CreatePolicy	allow pgo create policy
CreateSchedule	allow pgo create schedule
${\bf Create Upgrade}$	allow pgo upgrade
CreateUser	allow pgo create user
${\bf Delete Backup}$	allow pgo delete backup
${\bf Delete Benchmark}$	allow pgo delete benchmark
DeleteCluster	allow pgo delete cluster
${\bf DeletePgbouncer}$	allow pgo delete pgbouncer
${\bf DeletePgpool}$	allow pgo delete pgpool
DeletePolicy	allow pgo delete policy
DeleteSchedule	allow $pgo\ delete\ schedule$
${\bf Delete Upgrade}$	allow pgo delete upgrade
DeleteUser	allow pgo delete user
DfCluster	allow $pgo df$
Label	allow pgo label
Load	allow pgo load
Ls	allow pgo ls
Reload	allow pgo reload
Restore	allow pgo restore
${\bf Restore Dump}$	allow pgo restore for pgdumps
ShowBackup	allow pgo show backup
${\bf ShowBenchmark}$	allow $pgo\ show\ benchmark$
ShowCluster	allow pgo show cluster
ShowConfig	allow pgo show config
ShowPolicy	allow pgo show policy
$\operatorname{ShowPVC}$	allow pgo show pvc
ShowSchedule	allow $pgo\ show\ schedule$
${\bf Show Name space}$	allow $pgo\ show\ namespace$
${\bf ShowUpgrade}$	allow $pgo\ show\ upgrade$
${\bf ShowWorkflow}$	allow $pgo\ show\ workflow$
Status	allow pgo status
TestCluster	allow pgo test
${\bf UpdateCluster}$	allow pgo update cluster
User	allow pgo user
Version	allow pgo version

If the user is unauthorized for a pgo command, the user will get back this response:

```
Error: Authentication Failed: 401
```

Making Security Changes

The Operator today requires you to make Operator user security changes in the property and property files, and for those changes to take effect you are required to re-deploy the Operator:

```
make deployoperator
```

This will recreate the pgo-config ConfigMap that stores these files and is mounted by the Operator during its initialization.

API Security

The Operator REST API is secured with keys stored in the pgo.tls Secret. Adjust the default keys to meet your security requirements using your own keys. The pgo.tls Secret is created when you run:

```
make deployoperator
```

The keys are generated when the RBAC script is executed by the cluster admin:

```
make installrbac
```

The the Secret keys within the pgo-apiserver container are mounted at:

```
/apiserver.local.config/certificates/tls.crt
/apiserver.local.config/certificates/tls.key
```

You can view the TLS secret using:

```
kubectl get secret pgo.tls -n pgo
```

or oc get secret pgo.tls -n pgo

The key and cert that are generated by the default installation are found here:

```
$PGOROOT/conf/postgres-operator/server.crt
$PGOROOT/conf/postgres-operator/server.key
```

The key and cert are generated using the deploy/gen-api-keys.sh script. That script gets executed when running:

```
make installrbac
```

You can extract the server key and server crt from the Secret using the following:

```
oc get secret pgo.tls -n $PGO_OPERATOR_NAMESPACE -o jsonpath='{.data.tls\.key}' | base64 --decode > /tmp/server.key
oc get secret pgo.tls -n $PGO_OPERATOR_NAMESPACE -o jsonpath='{.data.tls\.crt}' | base64 --decode > /tmp/server.crt
```

This server key and server crt can then be used to access the pqo-apiserver REST API.

Upgrading the Operator

Various Operator releases will require action by the Operator administrator of your organization in order to upgrade to the next release of the Operator. Some upgrade steps are automated within the Operator but not all are possible at this time.

This section of the documentation shows specific steps required to the latest version from the previous version.

Upgrading to Version 3.5.0 From Previous Versions

- For clusters created in prior versions that used pgbackrest, you will be required to first create a pgbasebackup for those clusters, and after upgrading to Operator 3.5, you will need to restore those clusters from the pgbasebackup into a new cluster with -pgbackrest enabled, this is due to the new pgbackrest shared repository being implemented in 3.5. This is a breaking change for anyone that used pgbackrest in Operator versions prior to 3.5.
- The pgingest CRD is removed. You will need to manually remove it from any deployments of the operator after upgrading to this version. This includes removing ingest related permissions from the pgorole file. Additionally, the API server now removes the ingest related API endpoints.
- Primary and replica labels are only applicable at cluster creation and are not updated after a cluster has executed a failover. A new service-name label is applied to PG cluster components to indicate whether a deployment/pod is a primary or replica. service-name is also the label now used by the cluster services to route with. This scheme allows for an almost immediate failover promotion and avoids the pod having to be bounced as part of a failover. Any existing PostgreSQL clusters will need to be updated to specify them as a primary or replica using the new service-name labeling scheme.
- The autofail label was moved from deployments and pods to just the pgcluster CRD to support autofail toggling.
- The storage configurations in *pgo.yaml* support the MatchLabels attribute for NFS storage. This will allow users to have more than a single NFS backend,. When set, this label (key=value) will be used to match the labels on PVs when a PVC is created.
- The UpdateCluster permission was added to the sample provide file to support the new propert update CLI command. It was also added to the propert file.
- The pgo.yaml adds the PreferredFailoverNode setting. This is a Kubernetes selector string (e.g. key=value). This value if set, will cause fail-over targets to be preferred based on the node they run on if that node is in the set of preferred.
- The ability to select nodes based on a selector string was added. For this to feature to be used, multiple replicas have to be in a ready state, and also at the same replication status. If those conditions are not met, the default fail-over target selection is used.
- The pgo.yaml file now includes a new storage configuration, XlogStorage, which when set will cause the xlog volume to be allocated using this storage configuration. If not set, the PrimaryStorage configuration will be used.
- The pgo.yaml file now includes a new storage configuration, BackrestStorage, will cause the pgbackrest shared repository volume to be allocated using this storage configuration.
- The pgo.yaml file now includes a setting, AutofailReplaceReplica, which will enable or disable whether a new replica is created as part of a fail-over. This is turned off by default.

See the GitHub Release notes for the features and other notes about a specific release.