X-Mem 2.1.7

Generated by Doxygen 1.8.6

Thu Apr 16 2015 13:24:55

Contents

1	REA	DME			1
2	Hier	archica	l Index		7
	2.1	Class	Hierarchy		7
3	Clas	s Index			9
	3.1	Class	List		9
4	File	Index			11
	4.1	File Lis	st		11
5	Clas	s Docu	mentation	1 1	13
	5.1	xmem	::Parser::A	ction Struct Reference	13
		5.1.1	Member	Function Documentation	13
			5.1.1.1	finished	13
			5.1.1.2	perform	13
	5.2	xmem:	::Arg Struc	t Reference	14
		5.2.1	Detailed	Description	14
	5.3	xmem	::Benchma	rk Class Reference	15
		5.3.1	Detailed	Description	17
		5.3.2	Construc	tor & Destructor Documentation	17
			5.3.2.1	Benchmark	17
		5.3.3	Member	Function Documentation	17
			5.3.3.1	_run_core	17
			5.3.3.2	_start_power_threads	18
			5.3.3.3	_stop_power_threads	18
			5.3.3.4	getAverageDRAMPower	18
			5.3.3.5	getAverageMetric	18
			5.3.3.6	getChunkSize	18
			5.3.3.7	getCPUNode	18
			5.3.3.8	getIterations	19
			5.3.3.9	getLen	19
			E 2 2 10	actNomNodo	10

iv CONTENTS

		5.3.3.11	getMetricOnIter	19
		5.3.3.12	getMetricUnits	19
		5.3.3.13	getName	19
		5.3.3.14	getNumThreads	20
		5.3.3.15	getPatternMode	20
		5.3.3.16	getPeakDRAMPower	20
		5.3.3.17	getRWMode	20
		5.3.3.18	getStrideSize	20
		5.3.3.19	hasRun	20
		5.3.3.20	isValid	20
		5.3.3.21	run	21
	5.3.4	Member	Data Documentation	21
		5.3.4.1	_average_dram_power_socket	21
		5.3.4.2	_averageMetric	21
		5.3.4.3	_chunk_size	21
		5.3.4.4	_cpu_node	21
		5.3.4.5	_dram_power_readers	21
		5.3.4.6	_dram_power_threads	21
		5.3.4.7	_hasRun	21
		5.3.4.8	_iterations	21
		5.3.4.9	_len	21
		5.3.4.10	_mem_array	22
		5.3.4.11	_mem_node	22
		5.3.4.12	_metricOnlter	22
		5.3.4.13	_metricUnits	22
		5.3.4.14	_name	22
		5.3.4.15	_num_worker_threads	22
		5.3.4.16	_obj_valid	22
		5.3.4.17	_pattern_mode	22
		5.3.4.18	_peak_dram_power_socket	22
		5.3.4.19	_rw_mode	22
		5.3.4.20	_stride_size	22
		5.3.4.21	_warning	23
5.4	xmem:	:Benchma	rkManager Class Reference	23
	5.4.1	Detailed	Description	23
	5.4.2	Construc	tor & Destructor Documentation	23
		5.4.2.1	BenchmarkManager	23
	5.4.3	Member	Function Documentation	23
		5.4.3.1	runAll	23
		5.4.3.2	runLatencyBenchmarks	24

CONTENTS

		5.4.3.3	runThroughputBenchmarks	24
5.5	xmem:	::Configura	tor Class Reference	24
	5.5.1	Detailed I	Description	25
	5.5.2	Member I	Function Documentation	26
		5.5.2.1	configureFromInput	26
		5.5.2.2	extensionsEnabled	28
		5.5.2.3	getIterationsPerTest	28
		5.5.2.4	getNumWorkerThreads	28
		5.5.2.5	getOutputFilename	28
		5.5.2.6	getStartingTestIndex	28
		5.5.2.7	getWorkingSetSizePerThread	28
		5.5.2.8	isNUMAEnabled	29
		5.5.2.9	latencyTestSelected	29
		5.5.2.10	runExtDelayInjectedLoadedLatencyBenchmark	29
		5.5.2.11	setUseOutputFile	29
		5.5.2.12	throughputTestSelected	29
		5.5.2.13	useChunk128b	29
		5.5.2.14	useChunk256b	29
		5.5.2.15	useChunk32b	30
		5.5.2.16	useChunk64b	30
		5.5.2.17	useLargePages	30
		5.5.2.18	useOutputFile	30
		5.5.2.19	useRandomAccessPattern	30
		5.5.2.20	useReads	30
		5.5.2.21	useSequentialAccessPattern	30
		5.5.2.22	useStrideN1	31
		5.5.2.23	useStrideN16	31
		5.5.2.24	useStrideN2	31
		5.5.2.25	useStrideN4	31
		5.5.2.26	useStrideN8	31
		5.5.2.27	useStrideP1	31
		5.5.2.28	useStrideP16	31
		5.5.2.29	useStrideP2	32
		5.5.2.30	useStrideP4	32
		5.5.2.31	useStrideP8	32
		5.5.2.32	useWrites	32
				32
5.6	xmem:	::Stats::Cou	untOptionsAction Class Reference	32
	5.6.1	Construct		33
		5.6.1.1	CountOptionsAction	33

vi CONTENTS

	5.6.2	Member F	Function Documentation	33
		5.6.2.1	perform	33
5.7	xmem::	:Descriptor	Struct Reference	33
	5.7.1	Detailed D	Description	34
	5.7.2	Member E	Data Documentation	34
		5.7.2.1	check_arg	34
		5.7.2.2	help	34
		5.7.2.3	index	34
		5.7.2.4	longopt	35
		5.7.2.5	shortopt	35
		5.7.2.6	type	35
5.8	xmem::	:ExampleA	rg Class Reference	35
5.9	xmem::	:PrintUsage	eImplementation::FunctionWriter< Function $>$ Struct Template Reference	36
5.10	xmem::	:PrintUsage	eImplementation::IStringWriter Struct Reference	36
5.11	xmem::	:LatencyBe	enchmark Class Reference	37
	5.11.1	Detailed D	Description	37
	5.11.2	Member F	Function Documentation	38
		5.11.2.1	_run_core	38
		5.11.2.2	getAvgLoadMetric	38
		5.11.2.3	getLoadMetricOnIter	38
	5.11.3	Member E	Data Documentation	38
		5.11.3.1	_averageLoadMetric	38
		5.11.3.2	_loadMetricOnIter	38
5.12	xmem::	:LatencyWo	orker Class Reference	38
	5.12.1	Detailed D	Description	39
	5.12.2	Construct	or & Destructor Documentation	39
		5.12.2.1	LatencyWorker	39
5.13	xmem::	:PrintUsage	elmplementation::LinePartIterator Class Reference	39
	5.13.1	Member F	Function Documentation	40
		5.13.1.1	next	40
		5.13.1.2	nextRow	40
		5.13.1.3	nextTable	40
5.14	xmem::	:PrintUsage	elmplementation::LineWrapper Class Reference	41
	5.14.1	Construct	or & Destructor Documentation	41
		5.14.1.1	LineWrapper	41
	5.14.2	Member F	Function Documentation	41
		5.14.2.1	process	41
5.15	xmem::	:LoadWork	er Class Reference	41
			Description	42
	5.15.2	Construct	or & Destructor Documentation	42

CONTENTS vii

		5.15.2.1 LoadWorker	42
		5.15.2.2 LoadWorker	42
5.16	xmem::	MemoryWorker Class Reference	43
	5.16.1	Detailed Description	44
	5.16.2	Constructor & Destructor Documentation	44
		5.16.2.1 MemoryWorker	44
	5.16.3	Member Function Documentation	44
		5.16.3.1 getAdjustedTicks	44
		5.16.3.2 getBytesPerPass	44
		5.16.3.3 getElapsedDummyTicks	45
		5.16.3.4 getElapsedTicks	45
		5.16.3.5 getLen	45
		5.16.3.6 getPasses	45
		5.16.3.7 hadWarning	45
	5.16.4	Member Data Documentation	45
		5.16.4.1 _adjusted_ticks	45
		5.16.4.2 _bytes_per_pass	45
		5.16.4.3 _completed	45
		5.16.4.4 _cpu_affinity	46
		5.16.4.5 _elapsed_dummy_ticks	46
		5.16.4.6 _elapsed_ticks	46
		5.16.4.7 _len	46
		5.16.4.8 _mem_array	46
		5.16.4.9 _passes	46
		5.16.4.10 _warning	46
5.17	xmem::	MyArg Class Reference	46
5.18	xmem::	Option Class Reference	47
	5.18.1	Detailed Description	48
	5.18.2	Constructor & Destructor Documentation	48
		5.18.2.1 Option	48
		5.18.2.2 Option	48
	5.18.3	Member Function Documentation	49
		5.18.3.1 append	49
		5.18.3.2 count	49
		5.18.3.3 first	49
		5.18.3.4 isFirst	49
		5.18.3.5 isLast	49
		5.18.3.6 last	49
		5.18.3.7 next	50
		5.18.3.8 nextwrap	50

viii CONTENTS

		5.18.3.9 operator const Option *	50
		5.18.3.10 operator Option *	50
		5.18.3.11 operator=	51
		5.18.3.12 prev	51
		5.18.3.13 prevwrap	51
		5.18.3.14 type	51
	5.18.4	Member Data Documentation	51
		5.18.4.1 arg	51
		5.18.4.2 desc	51
		5.18.4.3 name	52
		5.18.4.4 namelen	52
5.19	xmem::	PrintUsageImplementation::OStreamWriter< OStream > Struct Template Reference	52
5.20	xmem::	Parser Class Reference	53
	5.20.1	Detailed Description	54
	5.20.2	Constructor & Destructor Documentation	54
		5.20.2.1 Parser	54
	5.20.3	Member Function Documentation	55
		5.20.3.1 error	55
		5.20.3.2 nonOptions	55
		5.20.3.3 nonOptionsCount	56
		5.20.3.4 optionsCount	56
		5.20.3.5 parse	56
5.21	xmem::	PowerReader Class Reference	57
	5.21.1	Detailed Description	58
	5.21.2	Constructor & Destructor Documentation	58
		5.21.2.1 PowerReader	58
	5.21.3	Member Function Documentation	59
		5.21.3.1 calculateMetrics	59
		5.21.3.2 clear	59
		5.21.3.3 clear_and_reset	59
		5.21.3.4 getAveragePower	59
		5.21.3.5 getLastSample	59
		5.21.3.6 getNumSamples	60
		5.21.3.7 getPeakPower	60
		5.21.3.8 getPowerTrace	60
		5.21.3.9 getPowerUnits	60
		5.21.3.10 getSamplingPeriod	60
		5.21.3.11 name	60
		5.21.3.12 stop	61
	5.21.4	Member Data Documentation	61

CONTENTS

		5.21.4.1 _average_power	61
		5.21.4.2 _cpu_affinity	61
		5.21.4.3 _name	61
		5.21.4.4 _num_samples	61
		5.21.4.5 _peak_power	61
		5.21.4.6 _power_trace	61
		5.21.4.7 _power_units	61
		5.21.4.8 _sampling_period	61
		5.21.4.9 _stop_signal	61
5.22	xmem:	PrintUsageImplementation Struct Reference	62
	5.22.1	Member Function Documentation	62
		5.22.1.1 isWideChar	62
5.23	xmem:	Runnable Class Reference	62
	5.23.1	Detailed Description	63
	5.23.2	Member Function Documentation	63
		5.23.2.1 _acquireLock	63
		5.23.2.2 _releaseLock	63
5.24	xmem:	Stats Struct Reference	64
	5.24.1	Detailed Description	65
	5.24.2	Constructor & Destructor Documentation	65
		5.24.2.1 Stats	65
	5.24.3	Member Function Documentation	65
		5.24.3.1 add	65
	5.24.4	Member Data Documentation	65
		5.24.4.1 buffer_max	65
		5.24.4.2 options_max	66
5.25	xmem:	Parser::StoreOptionAction Class Reference	66
	5.25.1	Constructor & Destructor Documentation	66
		5.25.1.1 StoreOptionAction	66
	5.25.2	Member Function Documentation	67
		5.25.2.1 finished	67
		5.25.2.2 perform	67
5.26	xmem:	PrintUsageImplementation::StreamWriter< Function, Stream > Struct Template Reference	67
5.27	xmem:	PrintUsageImplementation::SyscallWriter< Syscall > Struct Template Reference	68
5.28	xmem:	$PrintUsageImplementation:: Temporary Writer < Temporary > Struct \ Template \ Reference \ . \ .$	68
5.29	xmem:	Thread Class Reference	69
	5.29.1	Detailed Description	69
	5.29.2	Constructor & Destructor Documentation	69
		5.29.2.1 Thread	69
		5.29.2.2 ~Thread	69

X CONTENTS

		5.29.3	Member Function Documentation	70
			5.29.3.1 cancel	70
			5.29.3.2 completed	70
			5.29.3.3 create_and_start	70
			5.29.3.4 created	70
			5.29.3.5 getExitCode	70
			5.29.3.6 getTarget	70
			5.29.3.7 isThreadRunning	70
			5.29.3.8 isThreadSuspended	71
			5.29.3.9 join	71
			5.29.3.10 started	71
			5.29.3.11 validTarget	71
	5.30	xmem:	ThroughputBenchmark Class Reference	71
		5.30.1	Detailed Description	72
		5.30.2	Member Function Documentation	72
			5.30.2.1 _run_core	72
	5.31	xmem:	Timer Class Reference	72
		5.31.1	Detailed Description	72
		5.31.2	Member Function Documentation	73
			5.31.2.1 get_ns_per_tick	73
			5.31.2.2 get_ticks_per_sec	73
		5.31.3	Member Data Documentation	73
			5.31.3.1 _ns_per_tick	73
			5.31.3.2 _ticks_per_sec	73
•	En l	D = =		
6				75
	6.1			75
	0.0	6.1.1	·	75
	6.2			75
	0.0	6.2.1	•	75
	6.3		5 11	76
		6.3.1	·	76
	6.4			76
		6.4.1	·	76
	6.5		· · · · · · · · · · · · · · · · · · ·	77
		6.5.1	and the second s	77
	6.6		DelayInjectedLoadedLatencyBenchmark/delay_injected_benchmark_kernels.cpp File Refer-	77
		6.6.1	Detailed Description	77
	6.7		DelayInjectedLoadedLatencyBenchmark/DelayInjectedLoadedLatencyBenchmark.cpp File	77

CONTENTS xi

	6.7.1	Detailed Description	77
6.8	src/incl	ude/Benchmark.h File Reference	78
	6.8.1	Detailed Description	78
6.9	src/incl	ude/benchmark_kernels.h File Reference	78
	6.9.1	Detailed Description	85
6.10	src/incl	ude/BenchmarkManager.h File Reference	85
	6.10.1	Detailed Description	85
6.11	src/incl	ude/common.h File Reference	85
	6.11.1	Detailed Description	87
	6.11.2	Macro Definition Documentation	88
		6.11.2.1 BENCHMARK_DURATION_SEC	88
		6.11.2.2 DEFAULT_LARGE_PAGE_SIZE	88
		6.11.2.3 DEFAULT_NUM_L1_CACHES	88
		6.11.2.4 DEFAULT_NUM_L2_CACHES	88
		6.11.2.5 DEFAULT_NUM_L3_CACHES	88
		6.11.2.6 DEFAULT_NUM_L4_CACHES	88
		6.11.2.7 DEFAULT_NUM_LOGICAL_CPUS	88
		6.11.2.8 DEFAULT_NUM_NODES	88
		6.11.2.9 DEFAULT_NUM_PHYSICAL_CPUS	88
		6.11.2.10 DEFAULT_NUM_PHYSICAL_PACKAGES	88
		6.11.2.11 DEFAULT_NUM_WORKER_THREADS	88
		6.11.2.12 DEFAULT_PAGE_SIZE	88
		6.11.2.13 DEFAULT_WORKING_SET_SIZE_PER_THREAD	89
		6.11.2.14 EXT_DELAY_INJECTED_LOADED_LATENCY_BENCHMARK	89
		6.11.2.15 LATENCY_BENCHMARK_UNROLL_LENGTH	89
		6.11.2.16 MIN_ELAPSED_TICKS	89
		6.11.2.17 POWER_SAMPLING_PERIOD_MS	89
		6.11.2.18 THROUGHPUT_BENCHMARK_BYTES_PER_PASS	89
		6.11.2.19 USE_TIME_BASED_BENCHMARKS	89
		6.11.2.20 USE_TSC_TIMER	89
6.12	src/incl	ude/Configurator.h File Reference	89
	6.12.1	Detailed Description	90
6.13	src/incl	ude/ExampleArg.h File Reference	90
	6.13.1	Detailed Description	90
6.14		ude/ext/DelayInjectedLoadedLatencyBenchmark/delay_injected_benchmark_kernels.h File nce	90
	6.14.1	Detailed Description	93
6.15		ude/ext/DelayInjectedLoadedLatencyBenchmark/DelayInjectedLoadedLatencyBenchmark.h ference	93
	6.15.1	Detailed Description	93

xii CONTENTS

6.16	src/include/LatencyBenchmark.h File Reference	93
	6.16.1 Detailed Description	94
6.17	src/include/LatencyWorker.h File Reference	94
	6.17.1 Detailed Description	94
6.18	src/include/LoadWorker.h File Reference	94
	6.18.1 Detailed Description	94
6.19	src/include/MemoryWorker.h File Reference	94
	6.19.1 Detailed Description	95
6.20	src/include/MyArg.h File Reference	95
	6.20.1 Detailed Description	95
6.21	src/include/optionparser.h File Reference	95
	6.21.1 Detailed Description	96
6.22	src/include/PowerReader.h File Reference	99
	6.22.1 Detailed Description	99
6.23	src/include/Runnable.h File Reference	99
	6.23.1 Detailed Description	99
6.24	src/include/Thread.h File Reference	100
	6.24.1 Detailed Description	100
6.25	src/include/ThroughputBenchmark.h File Reference	100
	6.25.1 Detailed Description	100
6.26	src/include/Timer.h File Reference	100
	6.26.1 Detailed Description	101
6.27	src/include/win/win_common_third_party.h File Reference	101
	6.27.1 Detailed Description	101
6.28	src/include/win/win_CPdhQuery.h File Reference	101
	6.28.1 Detailed Description	101
6.29	src/include/win/WindowsDRAMPowerReader.h File Reference	
	6.29.1 Detailed Description	
6.30	src/LatencyBenchmark.cpp File Reference	
	6.30.1 Detailed Description	
6.31	src/LatencyWorker.cpp File Reference	
	6.31.1 Detailed Description	
6.32	src/LoadWorker.cpp File Reference	
	6.32.1 Detailed Description	
6.33	src/main.cpp File Reference	
	6.33.1 Detailed Description	102
6.34		103
	6.34.1 Detailed Description	
6.35	src/PowerReader.cpp File Reference	
	6.35.1 Detailed Description	103

CONTENTS xiii

Index		106
	6.41.1 Detailed Description	105
6.41	src/win/WindowsDRAMPowerReader.cpp File Reference	104
	6.40.1 Detailed Description	104
6.40	src/win/win_common_third_party.cpp File Reference	104
	6.39.1 Detailed Description	104
6.39	src/Timer.cpp File Reference	104
	6.38.1 Detailed Description	104
6.38	src/ThroughputBenchmark.cpp File Reference	104
	6.37.1 Detailed Description	104
6.37	src/Thread.cpp File Reference	103
	6.36.1 Detailed Description	103
6.36	src/Runnable.cpp File Reference	103

Chapter 1

README

X-Mem: Extensible Memory Benchmarking Tool v2.1.7

The flexible open-source research tool for characterizing memory hierarchy throughput, latency, and power.

Originally authored by Mark Gottscho (Email: mgottscho@ucla.edu) as a Summer 2014 intern at Microsoft Research, Redmond, WA.

This project is under active development. Stay tuned for more updates.

PROJECT REVISION DATE: April 16, 2015.

LICENSE

The MIT License (MIT)

Copyright (c) 2015 Microsoft

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

FEATURES

This tool is provided as open source with the hope of being useful to the broader research and development community. Here are some of X-Mem's features.

Flexibility: Easy reconfiguration for different combinations of tests

- · Working sets in increments of 4KB, allowing cache up to main memory-level benchmarking
- NUMA support
- · Multi-threading support
- Large page support

2 README

Extensibility: modularity via C++ object-oriented principles

- · Supports rapid addition of new benchmark kernel routines
- · Example: stream triad algorithm, impact of false sharing, etc. are possible with minor changes

Cross-platform: Currently implemented for Windows and GNU/Linux on x86-64 CPUs

- · Designed to allow straightforward porting to other operating systems and ISAs
- · GNU/Linux on ARM port planned

Memory throughput:

- · Accurate measurement of sustained memory throughput to all levels of cache and memory
- · Regular access patterns: forward & reverse sequential as well as strides of 2, 4, 8, and 16 words
- Random access patterns
- · Read and write
- · 32, 64, 128, 256-bit width memory instructions

Memory latency:

- · Accurate measurement of round-trip memory latency to all levels of cache and memory
- · Loaded and unloaded latency via use of multithreaded load generation

Memory power:

- · Currently collecting DRAM power via custom driver exposed in Windows performance counter API
- · Support custom power instrumentation through a simple interface that end-users can implement

Documentation:

· Extensive Doxygen source code comments, PDF manual, HTML

INCLUDED EXTENSIONS (under src/include/ext and src/ext directories):

• Loaded latency benchmark variant with load delays inserted as nop instructions between memory instructions. This is done for 64-bit chunks, forward sequential read load threads only at the moment.

For feature requests, please refer to the contact information at the end of this README.

RUNTIME PREREQUISITES

There are a few runtime prerequisites in order for the software to run correctly.

HARDWARE:

• Intel x86-64 CPU supporting AVX extensions (Sandy Bridge or later).

WINDOWS:

Microsoft Windows 64-bit, 8.0 or later, Server 2012 or later.

- Microsoft Visual C++ 2013 Redistributables (64-bit)
- Potentially, Administrator privileges, in order to:
 - use large pages, if the –large_pages option is selected (see USAGE, below)
 - The first time you use -large_pages on a given Windows machine, you may need to ensure that your Windows user account has the necessary rights to allow lockable memory pages. To do this on Windows 8, run gpedit.msc -> Local Computer Policy -> Computer Configuration -> Windows Settings -> Security Settings -> Local Policies -> User Rights Assignment -> Add your username to "Lock pages in memory". Then log out and then log back in.
 - use the PowerReader interface, depending on end-user implementation
 - elevate thread priority and pin threads to logical CPUs for improved performance and benchmarking consistency

GNU/LINUX:

- GNU utilities with support for C++11. Tested with gcc 4.8.2 on Ubuntu 14.04 LTS.
- libhugetlbfs. You can obtain it at http://libhugetlbfs.sourceforge.net. On Ubuntu systems, you can install using "sudo apt-get install libhugetlbfs0".
- Potentially, administrator privileges, if you plan to use the -large_pages option.
 - During runtime, if the –large_pages option is selected, you may need to first manually ensure that large pages are available from the OS. This can be done by running "hugeadm --pool-list". It is recommended to set minimum pool to 1GB (in order to measure DRAM effectively). If needed, this can be done by running "hugeadm --pool-pages-min 2MB:512". Alternatively, run the linux_setup_runtime_hugetlbfs.sh script that is provided with X-Mem.

INSTALLATION

The only file that is needed to run on Windows is xmem-win.exe, and xmem-linux on GNU/Linux. It has no other dependencies aside from the system prerequisites listed above.

USAGE

USAGE: xmem [options]

Options: -a, -all Run all possible benchmark modes and settings supported by X-Mem. This will override any other relevant user inputs. Note that X-Mem may run for a long time. -c, -chunk_size A chunk size in bits to use for load traffic-generating threads used in throughput and loaded latency benchmarks. A chunk is the size of each memory access in a benchmark. Allowed values: 32, 64, 128, and 256. If no chunk sizes specified, use 64-bit chunks by default. Note that some chunk sizes may not be supported on some hardware. 32-bit chunks are not compatible with random-access patterns; these combinations of settings will be skipped if they occur. DEFAULT: 64 -e, extension Run an X-Mem extension defined by the user at build time. The integer argument specifies a single unique extension. This option may be included multiple times. Note that the extension behavior may or may not depend on the other X-Mem options as its semantics are defined by the extension author. -f, -output_file Generate an output file in CSV format using the given filename. -h, -help Print X-Mem usage and exit. -i, -base_test_index Base index for the first benchmark to run. This option is provided for user convenience in enumerating benchmark tests across several subsequent runs of X-Mem. DEFAULT: 1 -j, -num_worker_threads Number of worker threads to use in benchmarks. This may not exceed the number of logical CPUs in the system. For throughput benchmarks, this is the number of independent load-generating threads. For latency benchmarks, this is the number of independent load-generating threads plus one latency measurement thread. In latency benchmarks, 1 worker thread indicates no loading is applied. DEFAULT: 1 -I, -latency Unloaded or loaded latency benchmarking mode. If 1 thread is used, unloaded latency is measured using 64-bit random reads. Otherwise, 1 thread is always dedicated to the 64-bit random read latency measurement, and remaining threads are used for load traffic generation using access patterns, chunk sizes, etc. specified by other arguments. See the throughput option for more information on load traffic generation. -n, -iterations lterations per benchmark. Multiple independent iterations may be performed on each benchmark setting to ensure consistent results. DEFAULT: 1 -r, -random_access Use a random access 4 README

pattern for load traffic-generating threads used in throughput and loaded latency benchmarks. -s, -sequential access Use a sequential and/or strided access pattern for load traffic generating-threads used in throughput and loaded latency benchmarks. -t, -throughput Throughput benchmarking mode. Aggregate throughput is measured across all worker threads. Each load traffic-generating worker in a particular benchmark runs an identical kernel. Multiple distinct benchmarks may be run depending on the specified benchmark settings (e.g., aggregated 64-bit and 256-bit sequential read throughput using strides of 1 and -8 chunks). -u, -ignore numa Force uniform memory access (UMA) mode. This only has an effect in non-uniform memory access (NUMA) systems. Limits benchmarking to CPU and memory NUMA node 0 instead of all intra-node and inter-node combinations. This mode can be useful in situations where the user is not interested in cross-node effects or node asymmetry. This option may also be required if large pages are desired on GNU/Linux systems due to lack of NUMA support in current versions of hugetlbfs. See the large pages option. -v, -verbose Verbose mode increases the level of detail in X-Mem console reporting. -w, -working_set_size Working set size per worker thread in KB. This must be a multiple of 4KB. In all benchmarks, each worker thread works on its own "private" region of memory. For example, 4-thread throughput benchmarking with a working set size of 4 KB might result in measuring the aggregate throughput of four L1 caches corresponding to four physical cores, with no data sharing between threads. Similarly, an 8-thread loaded latency benchmark with a working set size of 64 MB would use 512 MB of memory in total for benchmarking, with no data sharing between threads. This would result in performance measurement of the shared DRAM physical interface, the shared L3 cache, etc. -L, -large pages Use large pages. This might enable better memory performance by reducing the translation-lookaside buffer (TLB) bottleneck. However, this is not supported on all systems. On GNU/-Linux, you need hugetlbfs support with pre-reserved huge pages prior to running X-Mem. On GNU/Linux, you also must use the ignore numa option, as hugetlbfs is not NUMA-aware at this time. -R, -reads Use memory read-based patterns in load traffic-generating threads. -W, -writes Use memory write-based patterns in load traffic-generating threads. -S, -stride size A stride size to use for load traffic-generating threads, specified in powers-of-two multiples of the chunk size(s). Allowed values: 1, -1, 2, -2, 4, -4, 8, -8, 16, -16. Positive indicates the forward direction (increasing addresses), while negative indicates the reverse direction.

If a given option is not specified, X-Mem defaults will be used where appropriate.

Print X-Mem usage message and exit. If -help or -h is specified, benchmarks will not run regardless of other options.

```
xmem --help
```

Run unloaded latency benchmarks with 5 iterations of each distinct benchmark setting. The chunk size of 32 bits and sequential access pattern options will be ignored as they only apply to load traffic-generating threads, which are unused here as the default number of worker threads is 1. Console reporting will be verbose.

```
xmem -1 --verbose -n5 --chunk_size=32 -s
```

Run throughput and loaded latency benchmarks on a per-thread working set size of 512 MB for a grand total of 1 GB of memory space. Use chunk sizes of 32 and 256 bits for load traffic-generating threads, and ignore NUMA effects. Number the first benchmark test starting at 101 both in console reporting and CSV file output (results.csv).

```
xmem -t --latency -w524288 -f results.csv -c32 -c256 -i 101 -u -j2
```

Run 3 iterations of throughput and loaded latency on a working set of 128 KB per thread. Use 4 worker threads in total. For load traffic-generating threads, use all combinations of read and write memory accesses, random-access patterns, forward sequential, and strided patterns of size -4 and -16 chunks. Ignore NUMA effects in the system and use large pages. Finally, increase verbosity of console output. Finally, run custom user extensions with indices 0 and 1. Note that these may not necessarily obey other input parameters as their behavior is defined by the extension author.

```
xmem -w128 -n3 -j4 -l -t --extension=0 -e1 -s -S1 -S-4 -r -S16 -R -W -u
```

-L -v

Run EVERYTHING and dump results to file.

```
xmem -a -v -ftest.csv
```

Have fun! =]

BUILDING FROM SOURCE

Before building the source, enable and disable the relevant compile-time options in src/include/common.h, under the section "User-configurable compilation configuration". Please read the comments by each #define statement to understand the context of each option.

After you have set the desired compile-time options, build the source. On Windows, running build-win.bat should suffice. On GNU/Linux, run build-linux.sh.

If you customize your build, make sure you use the "Release" mode for your OS. Do not include debug capabilities as it can dramatically affect performance of the benchmarks, leading to pessimistic results.

BUILD PREREQUISITES

There are a few software build prerequisites, depending on your platform.

WINDOWS:

- · Any version of Visual Studio 2013 64-bit (also known as version 12.0).
- Python 2.7. You can obtain it at http://www.python.org.
- SCons build system. You can obtain it at http://www.scons.org. Build tested with SCons 2.3.4.

GNU/LINUX:

- gcc with support for the C++11 standard. Tested with gcc version 4.8.2 on Ubuntu 14.04 LTS for x86-64.
- Python 2.7. You can obtain it at http://www.python.org. On Ubuntu systems, you can install using "sudo apt-get install python2.7". You may need some other Python 2.7 packages as well.
- SCons build system. You can obtain it at http://www.scons.org. On Ubuntu systems, you can install using "sudo apt-get install scons". Build tested with SCons 2.3.4.
- Kernel support for large (huge) pages. This support can be verified on your Linux installation by running "grep
 hugetlbfs /proc/filesystems". If you do not have huge page support in your kernel, you can build a kernel with
 the appropriate options switched on: "CONFIG_HUGETLB_PAGE" and "CONFIG_HUGETLBFS".
- libhugetlbfs. This is used for allocating large (huge) pages if the —large_pages runtime option is selected. You can obtain it at http://libhugetlbfs.sourceforge.net. On Ubuntu systems, you can install using "sudo apt-get install libhugetlbfs-dev".

DOCUMENTATION BUILD PREREQUISITES

The following tools are only needed for automatically regenerating source code documentation with HTML and PDF. WINDOWS:

- doxygen tool. You can obtain it at http://www.stack.nl/~dimitri/doxygen.
- LaTeX distribution. You can get a Windows distribution at http://www.miktex.org.
- make for Windows. You can obtain it at http://gnuwin32.sourceforge.net/packages/make.htm. You will have to manually add it to your Windows path.

GNU/LINUX:

- doxygen tool. You can obtain it at http://www.stack.nl/~dimitri/doxygen. On Ubuntu systems, you can install with "sudo apt-get install doxygen".
- LaTeX distribution. On Ubuntu systems, LaTeX distributed with doxygen should actually be sufficient. You can install with "sudo apt-get install doxygen-latex".
- make. This should be included on any GNU/Linux system.

6 README

SOURCE CODE DOCUMENTATION

The tool comes with built-in Doxygen comments in the source code, which can be used to generate both HTML and LaTeX —> PDF documentation. Documentation is maintained under the doc/ subdirectory. To build documentation after modifying the source, run build-docs-win.bat on Windows, or build-docs-linux.sh on GNU/Linux systems. Note that Doxygen and a LaTeX distribution must be installed on the system.

VERSION CONTROL

This project is under version control using git. Its master repository is hosted at https://github.com/-Microsoft/X-Mem.git. There is also another fork at https://github.com/nanocad-lab/X--Mem.git, which generally mirrors Microsoft's repository.

CONTACT, FEEDBACK, AND BUG REPORTS

For questions, comments, criticism, bug reports, and other feedback for this software, please contact Mark Gottscho via email at mgottscho@ucla.edu or via web at http://www.seas.ucla.edu/~gottscho.

For inquiries about this work while conducted at Microsoft, please contact Dr. Mohammed Shoaib at mohammed. - shoaib@microsoft.com or Dr. Sriram Govindan at srgovin@microsoft.com.

ACKNOWLEDGMENT

Mark Gottscho would like to thank Dr. Mohammed Shoaib of Microsoft Research and Dr. Sriram Govindan of Microsoft for their mentorship in the creation of this software. Further thanks to Dr. Bikash Sharma, Mark Santaniello, Mike Andrewartha, and Laura Caulfield of Microsoft for their contributions, feedback, and assistance. Thank you as well to Dr. Jie Liu of Microsoft Research, Dr. Badriddine Khessib and Dr. Kushagra Vaid of Microsoft, and Prof. Puneet Gupta of UCLA for giving me the opportunity to create this work. Finally, Mark would like to thank Dr. Fedor Pikus of Mentor Graphics for teaching him some useful HPC programming techniques.

Chapter 2

Hierarchical Index

2.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

xmem::Parser::Action	13
xmem::Parser::StoreOptionAction	66
xmem::Stats::CountOptionsAction	32
xmem::Arg	14
xmem::ExampleArg	35
xmem::MyArg	46
xmem::Benchmark	15
xmem::LatencyBenchmark	37
xmem::ThroughputBenchmark	
xmem::BenchmarkManager	23
xmem::Configurator	24
·	33
xmem::PrintUsageImplementation::IStringWriter	36
$xmem:: Print U sage Implementation:: Function Writer < Function > \dots $	
$xmem:: Print U sage Implementation:: OS tream Writer < OS tream > \dots $	
$xmem:: Print U sage Implementation:: Stream Writer < Function, Stream > \dots $	
xmem::PrintUsageImplementation::SyscallWriter< Syscall >	
$xmem:: Print Usage Implementation:: Temporary Writer < Temporary > \dots $	68
xmem::PrintUsageImplementation::TemporaryWriter Temporary >	68 39
xmem::PrintUsageImplementation::TemporaryWriter Temporary >	68 39 41
xmem::PrintUsageImplementation::TemporaryWriter Temporary xmem::PrintUsageImplementation::LinePartIterator *** xmem::PrintUsageImplementation::LineWrapper *** xmem::Option ***	68 39 41 47
xmem::PrintUsageImplementation::TemporaryWriter<	68 39 41 47 53
xmem::PrintUsageImplementation::TemporaryWriter<	68 39 41 47 53 62
xmem::PrintUsageImplementation::TemporaryWriter< Temporary	68 39 41 47 53 62 62
xmem::PrintUsageImplementation::TemporaryWriter Temporary xmem::PrintUsageImplementation::LinePartIterator xmem::PrintUsageImplementation::LineWrapper xmem::Option xmem::Parser xmem::PrintUsageImplementation xmem::Runnable xmem::MemoryWorker xmem::MemoryWorker	68 39 41 47 53 62 62 43
xmem::PrintUsageImplementation::TemporaryWriter Temporary xmem::PrintUsageImplementation::LinePartIterator xmem::PrintUsageImplementation::LineWrapper xmem::Option xmem::Parser xmem::PrintUsageImplementation xmem::Runnable xmem::MemoryWorker xmem::LatencyWorker	68 39 41 47 53 62 43 38
xmem::PrintUsageImplementation::TemporaryWriter< Temporary > xmem::PrintUsageImplementation::LinePartIterator xmem::PrintUsageImplementation::LineWrapper xmem::Option xmem::Parser xmem::PrintUsageImplementation xmem::Runnable xmem::MemoryWorker xmem::LatencyWorker xmem::LoadWorker	68 39 41 47 53 62 43 38 41
xmem::PrintUsageImplementation::TemporaryWriter< Temporary > xmem::PrintUsageImplementation::LinePartIterator xmem::PrintUsageImplementation::LineWrapper xmem::Option xmem::Parser xmem::PrintUsageImplementation xmem::Runnable xmem::MemoryWorker xmem::LatencyWorker xmem::LoadWorker xmem::PowerReader	68 39 41 47 53 62 43 38 41 57
xmem::PrintUsageImplementation::TemporaryWriter< Temporary > xmem::PrintUsageImplementation::LinePartIterator xmem::PrintUsageImplementation::LineWrapper xmem::Option xmem::Parser xmem::PrintUsageImplementation xmem::Runnable xmem::MemoryWorker xmem::LatencyWorker xmem::LatencyWorker xmem::PowerReader xmem::PowerReader	68 39 41 47 53 62 43 38 41 57
xmem::PrintUsageImplementation::TemporaryWriter< Temporary > xmem::PrintUsageImplementation::LinePartIterator xmem::PrintUsageImplementation::LineWrapper xmem::Option xmem::Parser xmem::PrintUsageImplementation xmem::Runnable xmem::MemoryWorker xmem::LatencyWorker xmem::LoadWorker xmem::PowerReader xmem::Stats xmem::Thread	68 39 41 47 53 62 43 38 41 57

8 **Hierarchical Index**

Chapter 3

Class Index

3.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

xmem::Parser::Action	13
Functions for checking the validity of option arguments	14
xmem::Benchmark	
Flexible abstract class for any memory benchmark	15
xmem::BenchmarkManager	
Manages running all benchmarks at a high level	23
xmem::Configurator	
Handles all user input interpretation and generates the necessary flags for running benchmarks	24
xmem::Stats::CountOptionsAction	32
xmem::Descriptor	
Describes an option, its help text (usage) and how it should be parsed	33
xmem::ExampleArg	35
xmem::PrintUsageImplementation::FunctionWriter< Function >	36
xmem::PrintUsageImplementation::IStringWriter	36
xmem::LatencyBenchmark	
A type of benchmark that measures memory latency via random pointer chasing. Loading may	
be provided with separate threads which access memory as quickly as possible using given	
access patterns	37
xmem::LatencyWorker	
Multithreading-friendly class to do memory loading	38
xmem::PrintUsageImplementation::LinePartIterator	39
xmem::PrintUsageImplementation::LineWrapper	41
xmem::LoadWorker	
Multithreading-friendly class to do memory loading	41
xmem::MemoryWorker	40
Multithreading-friendly class to run memory access kernels	43
xmem::MyArg	46
xmem::Option	47
A parsed option from the command line together with its argument if it has one	47
xmem::PrintUsageImplementation::OStreamWriter< OStream >	52
xmem::Parser	
Checks argument vectors for validity and parses them into data structures that are easier to work	EO
with	53
An abstract base class for measuring power from an arbitrary source. This class is runnable	
An abstract base class for measuring power from an arbitrary source. This class is furniable	

57

10 Class Index

xmem::Runnable	
A base class for any object that implements a thread-safe run() function for use by Thread objects	62
xmem::Stats	
Determines the minimum lengths of the buffer and options arrays used for Parser	64
xmem::Parser::StoreOptionAction	66
xmem::PrintUsageImplementation::StreamWriter< Function, Stream >	67
xmem::PrintUsageImplementation::SyscallWriter< Syscall >	68
xmem::PrintUsageImplementation::TemporaryWriter< Temporary >	68
xmem::Thread	
Nice wrapped thread interface independent of particular OS API	69
xmem::ThroughputBenchmark	
A type of benchmark that measures memory throughput	71
xmem::Timer	
This class abstracts some characteristics of simple high resolution stopwatch timer. However,	
due to the inability or complexity of abstracting shared hardware timers, this class does not	
actually provide start and stop functions	72

Chapter 4

File Index

4.1 File List

Here is a list of all documented files with brief descriptions:

src/Benchmark.cpp	
Implementation file for the Benchmark class	75
src/benchmark_kernels.cpp	
Implementation file for benchmark kernel functions for doing the actual work we care about. :) .	75
src/BenchmarkManager.cpp	
Implementation file for the BenchmarkManager class	76
src/common.cpp	
Implementation file for common preprocessor definitions, macros, functions, and global con-	
stants	76
src/Configurator.cpp	
Implementation file for the Configurator class and some helper data structures	77
src/LatencyBenchmark.cpp	
Implementation file for the LatencyBenchmark class	101
src/LatencyWorker.cpp	
Implementation file for the LatencyWorker class	102
src/LoadWorker.cpp	
Implementation file for the LoadWorker class	102
src/main.cpp	
Main entry point to the tool	102
src/MemoryWorker.cpp	400
Implementation file for the MemoryWorker class	103
src/PowerReader.cpp	400
Implementation file for the PowerReader class	103
src/Runnable.cpp	400
Implementation file for the Runnable class	103
src/Thread.cpp	103
Implementation file for the Thread class	103
Implementation file for the ThroughputBenchmark class	104
src/Timer.cpp	104
Implementation file for the Timer class	104
src/ext/DelayInjectedLoadedLatencyBenchmark/delay_injected_benchmark_kernels.cpp	104
Implementation file for benchmark kernel functions for the delay-injected loaded latency bench-	
mark	77
src/ext/DelayInjectedLoadedLatencyBenchmark/DelayInjectedLoadedLatencyBenchmark.cpp	- / /
Implementation file for the DelayInjectedLatencyBenchmark class	77
src/include/Benchmark.h	11
Header file for the Benchmark class	78

12 File Index

src/include/benchmark kernels.h	
Header file for benchmark kernel functions for doing the actual work we care about. :)	78
src/include/BenchmarkManager.h	
Header file for the BenchmarkManager class	85
src/include/build_datetime.h	??
src/include/common.h	
Header file for common preprocessor definitions, macros, functions, and global constants	85
src/include/Configurator.h	
Header file for the Configurator class and some helper data structures	89
src/include/ExampleArg.h	
Slightly-modified third-party code related to OptionParser	90
src/include/LatencyBenchmark.h	
Header file for the LatencyBenchmark class	93
src/include/LatencyWorker.h	
Header file for the LatencyWorker class	94
src/include/LoadWorker.h	
Header file for the LoadWorker class	94
src/include/MemoryWorker.h	
Header file for the MemoryWorker class	94
src/include/MyArg.h	
Extensions to third-party optionparser-related code	95
src/include/optionparser.h	
This is the only file required to use The Lean Mean C++ Option Parser. Just #include it and	
you're set	95
src/include/PowerReader.h	
Header file for the PowerReader class	99
src/include/Runnable.h	
Header file for the Runnable class	99
src/include/Thread.h	
Header file for the Thread class	100
src/include/ThroughputBenchmark.h	
Header file for the ThroughputBenchmark class	100
src/include/Timer.h	. • •
Header file for the Timer class	100
src/include/ext/DelayInjectedLoadedLatencyBenchmark/delay injected benchmark kernels.h	
Header file for benchmark kernel functions with integrated delays for doing the actual work we	
care about.:)	90
src/include/ext/DelayInjectedLoadedLatencyBenchmark/DelayInjectedLoadedLatencyBenchmark.h	
Header file for the DelayInjectedLoadedLatencyBenchmark class	93
src/include/win/win_common_third_party.h	50
Header file for some third-party helper code for working with Windows APIs	101
src/include/win/win_CPdhQuery.h	10
Header and implementation file for some third-party code for measuring Windows OS-exposed	
performance counters	101
src/include/win/WindowsDRAMPowerReader.h	10
Header file for the WindowsDRAMPowerReader class	101
src/win/win_common_third_party.cpp	10
Implementation file for some third-party helper code for working with Windows APIs	104
· · · · · · · · · · · · · · · · · · ·	104
	104
src/win/WindowsDRAMPowerReader.cpp	10
Implementation file for the WindowsDRAMPowerReader class	104

Chapter 5

Class Documentation

5.1 xmem::Parser::Action Struct Reference

Inheritance diagram for xmem::Parser::Action:



Public Member Functions

• virtual bool perform (Option &)

Called by Parser::workhorse() for each Option that has been successfully parsed (including unknown options if they have a Descriptor whose Descriptor::check_arg does not return ARG_ILLEGAL.

• virtual bool finished (int numargs, const char **args)

Called by Parser::workhorse() after finishing the parse.

5.1.1 Member Function Documentation

5.1.1.1 virtual bool xmem::Parser::Action::finished (int numargs, const char ** args) [inline], [virtual]

Called by Parser::workhorse() after finishing the parse.

Parameters

numargs	the number of non-option arguments remaining
args	pointer to the first remaining non-option argument (if numargs $>$ 0).

Returns

false iff a fatal error has occurred.

Reimplemented in xmem::Parser::StoreOptionAction.

5.1.1.2 virtual bool xmem::Parser::Action::perform (Option &) [inline], [virtual]

Called by Parser::workhorse() for each Option that has been successfully parsed (including unknown options if they have a Descriptor whose Descriptor::check_arg does not return ARG_ILLEGAL.

14 Class Documentation

Returns false iff a fatal error has occured and the parse should be aborted.

Reimplemented in xmem::Parser::StoreOptionAction, and xmem::Stats::CountOptionsAction.

The documentation for this struct was generated from the following file:


· src/include/optionparser.h

5.2 xmem::Arg Struct Reference

Functions for checking the validity of option arguments.

```
#include <optionparser.h>
```

Inheritance diagram for xmem::Arg:



Static Public Member Functions

• static ArgStatus None (const Option &, bool)

For options that don't take an argument: Returns ARG_NONE.

static ArgStatus Optional (const Option & option, bool)

Returns ARG_OK if the argument is attached and ARG_IGNORE otherwise.

5.2.1 Detailed Description

Functions for checking the validity of option arguments.

The following example code can serve as starting place for writing your own more complex CheckArg functions:

```
struct Arg: public option::Arg
{
    static void printError(const char* msgl, const option::Option& opt, const char* msg2)
    {
        fprintf(stderr, "ERROR: %s", msgl);
        fwrite(opt.name, opt.namelen, 1, stderr);
        fprintf(stderr, "%s", msg2);
    }
    static option::ArgStatus Unknown(const option::Option& option, bool msg)
    {
        if (msg) printError("Unknown option '", option, "'\n");
        return option::ARG_ILLEGAL;
    }
    static option::ArgStatus Required(const option::Option& option, bool msg)
    {
        if (option.arg != 0)
            return option::ARG_OK;
        if (msg) printError("Option '", option, "' requires an argument\n");
        return option::ARG_ILLEGAL;
    }
    static option::ArgStatus NonEmpty(const option::Option& option, bool msg)
    {
        if (option.arg != 0 && option.arg[0] != 0)
            return option::ARG_OK;
        if (option.arg != 0 && option.arg[0] != 0)
            return option::ARG_OK;
    }
}
```

```
if (msg) printError("Option '", option, "' requires a non-empty argument\n");
    return option::ARG_ILLEGAL;
}

static option::ArgStatus Numeric(const option::Option& option, bool msg)
{
    char* endptr = 0;
    if (option.arg != 0 && strtol(option.arg, &endptr, 10)){};
    if (endptr != option.arg && *endptr == 0)
        return option::ARG_OK;

    if (msg) printError("Option '", option, "' requires a numeric argument\n");
    return option::ARG_ILLEGAL;
}
};
```

The documentation for this struct was generated from the following file:


src/include/optionparser.h

5.3 xmem::Benchmark Class Reference

Flexible abstract class for any memory benchmark.

```
#include <Benchmark.h>
```

Inheritance diagram for xmem::Benchmark:



Public Member Functions

Benchmark (void *mem_array, size_t len, uint32_t iterations, uint32_t num_worker_threads, uint32_t mem_node, uint32_t cpu_node, pattern_mode_t pattern_mode, rw_mode_t rw_mode, chunk_size_t chunk_size, int64_t stride_size, std::vector< PowerReader * > dram_power_readers, std::string metricUnits, std::string name)

Constructor.

virtual ∼Benchmark ()

Destructor.

• bool run ()

Runs the benchmark.

• void print_benchmark_header () const

Prints a header piece of information describing the benchmark to the console.

virtual void report_benchmark_info () const

Reports benchmark configuration details to the console.

virtual void report_results () const

Reports results to the console.

• bool isValid () const

Checks to see that the object is in a valid state.

bool hasRun () const

Checks to see if the benchmark has run.

• double getMetricOnIter (uint32_t iter) const

Extracts the metric of interest for a given iteration. Units are interpreted by the inheriting class.

16 Class Documentation

• double getAverageMetric () const

Gets the average benchmark metric across all iterations.

• std::string getMetricUnits () const

Gets the units of the metric for this benchmark.

double getAverageDRAMPower (uint32_t socket_id) const

Gets the average DRAM power over the benchmark.

• double getPeakDRAMPower (uint32_t socket_id) const

Gets the peak DRAM power over the benchmark.

• size_t getLen () const

Gets the length of the memory region in bytes. This is not necessarily the "working set size" depending on multithreading configuration.

• uint32 t getIterations () const

Gets the number of iterations for this benchmark.

• chunk_size_t getChunkSize () const

Gets the width of memory access used in this benchmark.

• int64 t getStrideSize () const

Gets the stride size for this benchmark.

• uint32_t getCPUNode () const

Gets the CPU NUMA node used in this benchmark.

uint32 t getMemNode () const

Gets the memory NUMA node used in this benchmark.

uint32 t getNumThreads () const

Gets the number of worker threads used in this benchmark.

std::string getName () const

Gets the human-friendly name of this benchmark.

pattern_mode_t getPatternMode () const

Gets the pattern mode for this benchmark.

rw_mode_t getRWMode () const

Gets the read/write mode for this benchmark.

Protected Member Functions

• virtual bool _run_core ()=0

The core benchmark function.

• bool _start_power_threads ()

Starts the DRAM power measurement threads.

bool _stop_power_threads ()

Stops the DRAM power measurement threads. This is a blocking call.

Protected Attributes

- void * mem array
- size t len
- · uint32_t _iterations
- uint32_t _num_worker_threads
- uint32_t _mem_node
- uint32_t _cpu_node
- pattern_mode_t _pattern_mode
- rw_mode_t _rw_mode
- chunk_size_t _chunk_size
- int64_t _stride_size

- std::vector< PowerReader * > _dram_power_readers
- std::vector< Thread * > _dram_power_threads
- std::vector< double > _metricOnIter
- double _averageMetric
- std::string metricUnits
- std::vector< double > _average_dram_power_socket
- std::vector< double > _peak_dram_power_socket
- std::string _name
- bool obj_valid
- bool hasRun
- bool _warning

5.3.1 Detailed Description

Flexible abstract class for any memory benchmark.

This class provides a generic interface for interacting with a benchmark. All benchmarks should be derived from this class.

5.3.2 Constructor & Destructor Documentation

5.3.2.1 Benchmark::Benchmark (void * mem_array, size_t len, uint32_t iterations, uint32_t num_worker_threads, uint32_t mem_node, uint32_t cpu_node, pattern_mode_t pattern_mode, rw_mode_t rw_mode, chunk_size_t chunk_size, int64_t stride_size, std::vector < PowerReader * > dram_power_readers, std::string metricUnits, std::string name)

Constructor.

Parameters

mem_array	A pointer to a contiguous chunk of memory that has been allocated for benchmarking among
	potentially several worker threads. This should be aligned to a 256-bit boundary.
len	Length of mem_array in bytes. This must be a multiple of 4 KB and should be at least the
	per-thread working set size times the number of worker threads.
iterations	Number of iterations of the complete benchmark. Used to average results and provide a
	measure of consistency and reproducibility.
passes_per	Number of passes to do in each iteration, to ensure timed section of code is "long enough".
iteration	
num_worker	The number of worker threads to use in the benchmark.
threads	
mem_node	The logical memory NUMA node used in the benchmark.
cpu_node	The logical CPU NUMA node to use for the benchmark.
pattern_mode	This indicates the general type of access pattern used, e.g. sequential or random.
rw_mode	This indicates the general type of read/write mix used, e.g. pure reads or pure writes.
chunk_size	Size of an individual memory access for load-generating worker threads.
stride_size	For sequential access patterns, this is the address distance between successive accesses,
	counted in chunks. Negative values indicate a reversed access pattern. A stride of +/-1 is
	purely sequential.
dram_power	A group of PowerReader objects for measuring DRAM power.
readers	
name	The name of the benchmark to use when reporting to console.

5.3.3 Member Function Documentation

5.3.3.1 virtual bool xmem::Benchmark::_run_core() [protected], [pure virtual]

The core benchmark function.

18 Class Documentation

Returns

True on success.

Implemented in xmem::LatencyBenchmark, and xmem::ThroughputBenchmark.

```
5.3.3.2 bool Benchmark::_start_power_threads() [protected]
```

Starts the DRAM power measurement threads.

Returns

True on success.

```
5.3.3.3 bool Benchmark::_stop_power_threads( ) [protected]
```

Stops the DRAM power measurement threads. This is a blocking call.

Returns

True on success.

5.3.3.4 double Benchmark::getAverageDRAMPower (uint32_t socket_id) const

Gets the average DRAM power over the benchmark.

Returns

The average DRAM power for a given socket in watts, or 0 if the data does not exist (power was unable to be collected or the benchmark has not run).

5.3.3.5 double Benchmark::getAverageMetric () const

Gets the average benchmark metric across all iterations.

Returns

The average metric.

5.3.3.6 chunk_size_t Benchmark::getChunkSize () const

Gets the width of memory access used in this benchmark.

Returns

The chunk size for this benchmark.

5.3.3.7 uint32_t Benchmark::getCPUNode () const

Gets the CPU NUMA node used in this benchmark.

Returns

The NUMA CPU node used in this benchmark.

5.3.3.8 uint32_t Benchmark::getIterations () const

Gets the number of iterations for this benchmark.

Returns

The number of iterations for this benchmark.

5.3.3.9 size_t Benchmark::getLen () const

Gets the length of the memory region in bytes. This is not necessarily the "working set size" depending on multi-threading configuration.

Returns

Length of the memory region in bytes.

5.3.3.10 uint32_t Benchmark::getMemNode () const

Gets the memory NUMA node used in this benchmark.

Returns

The NUMA memory node used in this benchmark.

5.3.3.11 double Benchmark::getMetricOnlter (uint32_t iter) const

Extracts the metric of interest for a given iteration. Units are interpreted by the inheriting class.

Parameters

iter Iteration to extract.

Returns

The metric on the iteration specified by the input.

5.3.3.12 std::string Benchmark::getMetricUnits () const

Gets the units of the metric for this benchmark.

Returns

A string representing the units for printing to console and file.

5.3.3.13 std::string Benchmark::getName () const

Gets the human-friendly name of this benchmark.

Returns

The benchmark test name.

20 Class Documentation

5.3.3.14 uint32_t Benchmark::getNumThreads () const Gets the number of worker threads used in this benchmark. Returns The number of worker threads used in this benchmark. 5.3.3.15 pattern_mode_t Benchmark::getPatternMode () const Gets the pattern mode for this benchmark. Returns The pattern mode enumerator. 5.3.3.16 double Benchmark::getPeakDRAMPower (uint32_t socket_id) const Gets the peak DRAM power over the benchmark. Returns The peak DRAM power for a given socket in watts, or 0 if the data does not exist (power was unable to be collected or the benchmark has not run). 5.3.3.17 rw_mode_t Benchmark::getRWMode () const Gets the read/write mode for this benchmark. Returns The read/write mix mode. 5.3.3.18 int64_t Benchmark::getStrideSize () const Gets the stride size for this benchmark. Returns The stride size in chunks. 5.3.3.19 bool Benchmark::hasRun () const Checks to see if the benchmark has run. Returns True if run() has already completed successfully. 5.3.3.20 bool Benchmark::isValid () const Checks to see that the object is in a valid state. Returns

True if the object was constructed correctly and can be used.

```
5.3.3.21 bool Benchmark::run ( )
```

Runs the benchmark.

Returns

True on benchmark success

5.3.4 Member Data Documentation

```
5.3.4.1 std::vector<double> xmem::Benchmark::_average_dram_power_socket [protected]
```

The average DRAM power in this benchmark, per socket.

```
5.3.4.2 double xmem::Benchmark::_averageMetric [protected]
```

Average metric over all iterations. Unit-less because any benchmark can set this metric as needed. It is up to the descendant class to interpret units.

```
5.3.4.3 chunk_size_t xmem::Benchmark::_chunk_size [protected]
```

Chunk size of memory accesses in this benchmark.

```
5.3.4.4 uint32_t xmem::Benchmark::_cpu_node [protected]
```

The CPU NUMA node used in this benchmark.

```
5.3.4.5 std::vector<PowerReader*> xmem::Benchmark::_dram_power_readers [protected]
```

The power reading objects for measuring DRAM power on a per-socket basis during the benchmark.

```
5.3.4.6 std::vector<Thread*> xmem::Benchmark::_dram_power_threads [protected]
```

The power reading threads for measuring DRAM power on a per-socket basis during the benchmark. These work with the DRAM power readers. Although they are worker threads, they are not counted as the "official" benchmarking worker threads.

```
5.3.4.7 bool xmem::Benchmark::_hasRun [protected]
```

Indicates whether the benchmark has run.

```
5.3.4.8 uint32_t xmem::Benchmark::_iterations [protected]
```

Number of iterations used in this benchmark.

```
5.3.4.9 size_t xmem::Benchmark::_len [protected]
```

Length of the memory region in bytes. This is not the working set size per thread!

22 Class Documentation

```
5.3.4.10 void* xmem::Benchmark::_mem_array [protected]
Pointer to the memory region to use in this benchmark.
5.3.4.11 uint32_t xmem::Benchmark::_mem_node [protected]
The memory NUMA node used in this benchmark.
5.3.4.12 std::vector<double> xmem::Benchmark::_metricOnlter [protected]
Metrics for each iteration of the benchmark. Unit-less because any benchmark can set this metric as needed. It is
up to the descendant class to interpret units.
5.3.4.13 std::string xmem::Benchmark::_metricUnits [protected]
String representing the units of measurement for the metric.
5.3.4.14 std::string xmem::Benchmark::_name [protected]
Name of this benchmark.
5.3.4.15 uint32_t xmem::Benchmark::_num_worker_threads [protected]
The number of worker threads used in this benchmark.
5.3.4.16 bool xmem::Benchmark::_obj_valid [protected]
Indicates whether this benchmark object is valid.
5.3.4.17 pattern_mode_t xmem::Benchmark::_pattern_mode [protected]
Access pattern mode.
5.3.4.18 std::vector<double> xmem::Benchmark:: peak dram power socket [protected]
The peak DRAM power in this benchmark, per socket.
5.3.4.19 rw_mode_t xmem::Benchmark::_rw_mode [protected]
Read/write mode.
```

5.3.4.20 int64_t xmem::Benchmark::_stride_size [protected]

Stride size in chunks for sequential pattern mode only.

```
5.3.4.21 bool xmem::Benchmark::_warning [protected]
```

Indicates whether the benchmarks results might be clearly questionable/inaccurate/incorrect due to a variety of factors.

The documentation for this class was generated from the following files:

- src/include/Benchmark.h
- src/Benchmark.cpp

5.4 xmem::BenchmarkManager Class Reference

Manages running all benchmarks at a high level.

```
#include <BenchmarkManager.h>
```

Public Member Functions

• BenchmarkManager (Configurator &config)

Constructor.

∼BenchmarkManager ()

Destructor.

· bool runAll ()

Runs all benchmark configurations (does not include extensions).

• bool runThroughputBenchmarks ()

Runs the throughput benchmarks.

• bool runLatencyBenchmarks ()

Runs the latency benchmark.

5.4.1 Detailed Description

Manages running all benchmarks at a high level.

5.4.2 Constructor & Destructor Documentation

5.4.2.1 BenchmarkManager::BenchmarkManager (Configurator & config)

Constructor.

Parameters

config The configuration object containing run-time options for this X-Mem execution instance.

5.4.3 Member Function Documentation

5.4.3.1 bool BenchmarkManager::runAll ()

Runs all benchmark configurations (does not include extensions).

Returns

True on success.

5.4.3.2 bool BenchmarkManager::runLatencyBenchmarks ()

Runs the latency benchmark.

Returns

True on benchmarking success.

5.4.3.3 bool BenchmarkManager::runThroughputBenchmarks ()

Runs the throughput benchmarks.

Returns

True on benchmarking success.

The documentation for this class was generated from the following files:

- src/include/BenchmarkManager.h
- src/BenchmarkManager.cpp

5.5 xmem::Configurator Class Reference

Handles all user input interpretation and generates the necessary flags for running benchmarks.

```
#include <Configurator.h>
```

Public Member Functions

• Configurator ()

Default constructor. A default configuration is set. You will want to run configureFromInput() most likely.

int32_t configureFromInput (int argc, char *argv[])

Specialized constructor for when you don't want to get config from input, and you want to pass it in directly.

• bool extensionsEnabled () const

Determines whether user extensions are enabled.

bool runExtDelayInjectedLoadedLatencyBenchmark () const

If included at compile-time, determines whether the delay-injected loaded latency benchmark extension should be run.

• bool latencyTestSelected () const

Indicates if the latency test has been selected.

bool throughputTestSelected () const

Indicates if the throughput test has been selected.

size_t getWorkingSetSizePerThread () const

Gets the working set size in bytes for each worker thread, if applicable.

bool useChunk32b () const

Determines if chunk size of 32 bits should be used in relevant benchmarks.

· bool useChunk64b () const

Determines if chunk size of 64 bits should be used in relevant benchmarks.

bool useChunk128b () const

Determines if chunk size of 128 bits should be used in relevant benchmarks.

• bool useChunk256b () const

Determines if chunk size of 256 bits should be used in relevant benchmarks.

• bool isNUMAEnabled () const

Determines if the benchmarks should test for all CPU/memory NUMA combinations.

• uint32_t getIterationsPerTest () const

Gets the number of iterations that should be run of each benchmark.

bool useRandomAccessPattern () const

Determines if throughput benchmarks should use a random access pattern.

• bool useSequentialAccessPattern () const

Determines if throughput benchmarks should use a sequential access pattern.

uint32_t getNumWorkerThreads () const

Gets the number of worker threads to use.

uint32 t getStartingTestIndex () const

Gets the numerical index of the first benchmark for CSV output purposes.

• std::string getOutputFilename () const

Gets the output filename to use, if applicable.

bool useOutputFile () const

Determines whether to generate an output CSV file.

void setUseOutputFile (bool use)

Changes whether an output file should be used.

• bool verboseMode () const

Determines whether X-Mem is in verbose mode.

· bool useLargePages () const

Determines whether X-Mem should use large pages.

· bool useReads () const

Determines whether reads should be used in throughput benchmarks.

• bool useWrites () const

Determines whether writes should be used in throughput benchmarks.

• bool useStrideP1 () const

Determines if a stride of +1 should be used in relevant benchmarks.

• bool useStrideN1 () const

Determines if a stride of -1 should be used in relevant benchmarks.

• bool useStrideP2 () const

Determines if a stride of +2 should be used in relevant benchmarks.

• bool useStrideN2 () const

Determines if a stride of -2 should be used in relevant benchmarks.

• bool useStrideP4 () const

Determines if a stride of +4 should be used in relevant benchmarks.

• bool useStrideN4 () const

Determines if a stride of -4 should be used in relevant benchmarks.

• bool useStrideP8 () const

Determines if a stride of +8 should be used in relevant benchmarks.

• bool useStrideN8 () const

Determines if a stride of -8 should be used in relevant benchmarks.

• bool useStrideP16 () const

Determines if a stride of +16 should be used in relevant benchmarks.

• bool useStrideN16 () const

Determines if a stride of -16 should be used in relevant benchmarks.

5.5.1 Detailed Description

Handles all user input interpretation and generates the necessary flags for running benchmarks.

5.5.2 Member Function Documentation

5.5.2.1 int32_t Configurator::configureFromInput (int argc, char *argv[])

Specialized constructor for when you don't want to get config from input, and you want to pass it in directly.

Parameters

runExtensions	Indicates if user-defined code should be run in addition to other standard functionality.
run_ext_delay	If true, and this extension is included at compile-time, run the delay-injected loaded latency
injected loaded-	benchmark extension.
_latency	bottomian extension.
iatency benchmark	
run_ext_stream-	If true, and this extension is included at compile-time, run the STREAM-like benchmark ex-
_benchmark	tension.
runLatency	Indicates latency benchmarks should be run.
runThroughput	Indicates throughput benchmarks should be run.
working_set	The total size of memory to test in all benchmarks, in bytes, per thread. This MUST be a
-	
size_per_thread	multiple of 4KB pages.
num_worker	The number of threads to use in throughput benchmarks, loaded latency benchmarks, and
threads	stress tests.
use_chunk_32b	If true, include 32-bit chunks for relevant benchmarks.
use_chunk_64b	If true, include 64-bit chunks for relevant benchmarks.
use_chunk	If true, include 128-bit chunks for relevant benchmarks.
128b	
use_chunk	If true, include 256-bit chunks for relevant benchmarks.
256b	
numa_enable	If true, then test all combinations of CPU/memory NUMA nodes.
iterations_per	For each unique benchmark test, this is the number of times to repeat it.
test	
use_random	If true, use random-access patterns in throughput benchmarks.
access_pattern	
use_sequential-	If true, use sequential-access patterns in throughput benchmarks.
_access_pattern	
starting_test	Numerical index to use for the first test. This is an aid for end-user interpreting and post-
index	processing of result CSV file, if relevant.
filename	Output filename to use.
use_output_file	If true, use the provided output filename.
verbose	If true, then X-Mem should be more verbose in its console reporting.
use_large	If true, then X-Mem will attempt to force usage of large pages.
pages	
use_reads	If true, then throughput benchmarks should use reads.
use_writes	If true, then throughput benchmarks should use writes.
use_stride_p1	If true, include stride of +1 for relevant benchmarks.
use_stride_n1	If true, include stride of -1 for relevant benchmarks.
use_stride_p2	If true, include stride of +2 for relevant benchmarks.
use_stride_n2	If true, include stride of -2 for relevant benchmarks.
use_stride_p4	If true, include stride of +4 for relevant benchmarks.
use_stride_n4	If true, include stride of -4 for relevant benchmarks.
use_stride_p8	If true, include stride of +8 for relevant benchmarks.
use_stride_n8	If true, include stride of -8 for relevant benchmarks.
use_stride_p16	If true, include stride of +16 for relevant benchmarks.
use_stride_n16	If true, include stride of -16 for relevant benchmarks. Configures the tool based on user's
	command-line inputs.

argc	The argc from main().
argv	The argv from main().

Returns

0 on success.

5.5.2.2 bool xmem::Configurator::extensionsEnabled () const [inline]

Determines whether user extensions are enabled.

Returns

True if extensions are enabled.

5.5.2.3 uint32_t xmem::Configurator::getIterationsPerTest() const [inline]

Gets the number of iterations that should be run of each benchmark.

Returns

The iterations for each test.

5.5.2.4 uint32_t xmem::Configurator::getNumWorkerThreads() const [inline]

Gets the number of worker threads to use.

Returns

The number of worker threads.

5.5.2.5 std::string xmem::Configurator::getOutputFilename() const [inline]

Gets the output filename to use, if applicable.

Returns

The output filename to use if useOutputFile() returns true. Otherwise return value is "".

5.5.2.6 uint32_t xmem::Configurator::getStartingTestIndex () const [inline]

Gets the numerical index of the first benchmark for CSV output purposes.

Returns

The starting benchmark index.

5.5.2.7 size_t xmem::Configurator::getWorkingSetSizePerThread()const [inline]

Gets the working set size in bytes for each worker thread, if applicable.

Returns

The working set size in bytes.

```
5.5.2.8 bool xmem::Configurator::isNUMAEnabled ( ) const [inline]
```

Determines if the benchmarks should test for all CPU/memory NUMA combinations.

Returns

True if all NUMA nodes should be tested.

```
5.5.2.9 bool xmem::Configurator::latencyTestSelected ( ) const [inline]
```

Indicates if the latency test has been selected.

Returns

True if the latency test has been selected to run.

```
5.5.2.10 bool xmem::Configurator::runExtDelayInjectedLoadedLatencyBenchmark( ) const [inline]
```

If included at compile-time, determines whether the delay-injected loaded latency benchmark extension should be run.

Returns

True if it should be run.

```
5.5.2.11 void xmem::Configurator::setUseOutputFile ( bool use ) [inline]
```

Changes whether an output file should be used.

Parameters

```
use If true, then use the output file.
```

```
5.5.2.12 bool xmem::Configurator::throughputTestSelected ( ) const [inline]
```

Indicates if the throughput test has been selected.

Returns

True if the throughput test has been selected to run.

```
5.5.2.13 bool xmem::Configurator::useChunk128b( )const [inline]
```

Determines if chunk size of 128 bits should be used in relevant benchmarks.

Returns

True if 128-bit chunks should be used.

```
5.5.2.14 bool xmem::Configurator::useChunk256b ( ) const [inline]
```

Determines if chunk size of 256 bits should be used in relevant benchmarks.

Returns

True if 256-bit chunks should be used.

```
5.5.2.15 bool xmem::Configurator::useChunk32b ( ) const [inline]
```

Determines if chunk size of 32 bits should be used in relevant benchmarks.

Returns

True if 32-bit chunks should be used.

```
5.5.2.16 bool xmem::Configurator::useChunk64b()const [inline]
```

Determines if chunk size of 64 bits should be used in relevant benchmarks.

Returns

True if 64-bit chunks should be used.

```
5.5.2.17 bool xmem::Configurator::useLargePages ( ) const [inline]
```

Determines whether X-Mem should use large pages.

Parameters

```
True | if large pages should be used.
```

```
5.5.2.18 bool xmem::Configurator::useOutputFile() const [inline]
```

Determines whether to generate an output CSV file.

Returns

True if an output file should be used.

```
5.5.2.19 bool xmem::Configurator::useRandomAccessPattern ( ) const [inline]
```

Determines if throughput benchmarks should use a random access pattern.

Returns

True if random access should be used.

```
5.5.2.20 bool xmem::Configurator::useReads() const [inline]
```

Determines whether reads should be used in throughput benchmarks.

Returns

True if reads should be used.

```
5.5.2.21 bool xmem::Configurator::useSequentialAccessPattern ( ) const [inline]
```

Determines if throughput benchmarks should use a sequential access pattern.

Returns

True if sequential access should be used.

```
5.5.2.22 bool xmem::Configurator::useStrideN1 ( ) const [inline]
Determines if a stride of -1 should be used in relevant benchmarks.
Returns
      True if a stride of -1 should be used.
5.5.2.23 bool xmem::Configurator::useStrideN16() const [inline]
Determines if a stride of -16 should be used in relevant benchmarks.
Returns
      True if a stride of -16 should be used.
5.5.2.24 bool xmem::Configurator::useStrideN2( ) const [inline]
Determines if a stride of -2 should be used in relevant benchmarks.
Returns
      True if a stride of -2 should be used.
5.5.2.25 bool xmem::Configurator::useStrideN4() const [inline]
Determines if a stride of -4 should be used in relevant benchmarks.
Returns
      True if a stride of -4 should be used.
5.5.2.26 bool xmem::Configurator::useStrideN8() const [inline]
Determines if a stride of -8 should be used in relevant benchmarks.
Returns
      True if a stride of -8 should be used.
5.5.2.27 bool xmem::Configurator::useStrideP1() const [inline]
Determines if a stride of +1 should be used in relevant benchmarks.
Returns
      True if a stride of +1 should be used.
5.5.2.28 bool xmem::Configurator::useStrideP16 ( ) const [inline]
Determines if a stride of +16 should be used in relevant benchmarks.
```

Generated on Thu Apr 16 2015 13:24:55 for X-Mem by Doxygen

True if a stride of +16 should be used.

Returns

5.5.2.29 bool xmem::Configurator::useStrideP2() const [inline]

Determines if a stride of +2 should be used in relevant benchmarks.

Returns

True if a stride of +2 should be used.

5.5.2.30 bool xmem::Configurator::useStrideP4() const [inline]

Determines if a stride of +4 should be used in relevant benchmarks.

Returns

True if a stride of +4 should be used.

5.5.2.31 bool xmem::Configurator::useStrideP8() const [inline]

Determines if a stride of +8 should be used in relevant benchmarks.

Returns

True if a stride of +8 should be used.

5.5.2.32 bool xmem::Configurator::useWrites () const [inline]

Determines whether writes should be used in throughput benchmarks.

Returns

True if writes should be used.

5.5.2.33 bool xmem::Configurator::verboseMode() const [inline]

Determines whether X-Mem is in verbose mode.

Returns

True if verbose mode is enabled.

The documentation for this class was generated from the following files:

- src/include/Configurator.h
- src/Configurator.cpp

5.6 xmem::Stats::CountOptionsAction Class Reference

Inheritance diagram for xmem::Stats::CountOptionsAction:

xmem::Parser::Action

| xmem::Stats::CountOptionsAction

Public Member Functions

- CountOptionsAction (unsigned *buffer_max_)
- bool perform (Option &)

Called by Parser::workhorse() for each Option that has been successfully parsed (including unknown options if they have a Descriptor whose Descriptor::check_arg does not return ARG_ILLEGAL.

5.6.1 Constructor & Destructor Documentation

5.6.1.1 xmem::Stats::CountOptionsAction::CountOptionsAction (unsigned * buffer_max_) [inline]

Creates a new CountOptionsAction that will increase *buffer_max_ for each parsed Option.

5.6.2 Member Function Documentation

```
5.6.2.1 bool xmem::Stats::CountOptionsAction::perform(Option & ) [inline], [virtual]
```

Called by Parser::workhorse() for each Option that has been successfully parsed (including unknown options if they have a Descriptor whose Descriptor::check_arg does not return ARG_ILLEGAL.

Returns false iff a fatal error has occured and the parse should be aborted.

Reimplemented from xmem::Parser::Action.

The documentation for this class was generated from the following file:

· src/include/optionparser.h

5.7 xmem::Descriptor Struct Reference

Describes an option, its help text (usage) and how it should be parsed.

```
#include <optionparser.h>
```

Public Attributes

· const unsigned index

Index of this option's linked list in the array filled in by the parser.

· const int type

Used to distinguish between options with the same index. See index for details.

• const char *const shortopt

Each char in this string will be accepted as a short option character.

const char *const longopt

The long option name (without the leading –).

const CheckArg check_arg

For each option that matches shortopt or longopt this function will be called to check a potential argument to the option.

const char * help

The usage text associated with the options in this Descriptor.

5.7.1 Detailed Description

Describes an option, its help text (usage) and how it should be parsed.

The main input when constructing an option::Parser is an array of Descriptors.

Example:

5.7.2 Member Data Documentation

5.7.2.1 const CheckArg xmem::Descriptor::check_arg

For each option that matches shortopt or longopt this function will be called to check a potential argument to the option.

This function will be called even if there is no potential argument. In that case it will be passed NULL as arg parameter. Do not confuse this with the empty string.

See CheckArg for more information.

5.7.2.2 const char* xmem::Descriptor::help

The usage text associated with the options in this Descriptor.

You can use option::printUsage() to format your usage message based on the help texts. You can use dummy Descriptors where shortopt and longopt are both the empty string to add text to the usage that is not related to a specific option.

See option::printUsage() for special formatting characters you can use in help to get a column layout.

Attention

Must be UTF-8-encoded. If your compiler supports C++11 you can use the "u8" prefix to make sure string literals are properly encoded.

5.7.2.3 const unsigned xmem::Descriptor::index

Index of this option's linked list in the array filled in by the parser.

Command line options whose Descriptors have the same index will end up in the same linked list in the order in which they appear on the command line. If you have multiple long option aliases that refer to the same option, give their descriptors the same index.

If you have options that mean exactly opposite things (e.g. -enable-foo and -disable-foo), you should also give them the same index, but distinguish them through different values for type. That way they end up in the same list and you can just take the last element of the list and use its type. This way you get the usual behaviour where switches later on the command line override earlier ones without having to code it manually.

Tip:

Use an enum rather than plain ints for better readability, as shown in the example at Descriptor.

5.7.2.4 const char* const xmem::Descriptor::longopt

The long option name (without the leading –).

If this Descriptor should not have a long option name, use the empty string "". NULL is not permitted here!

While shortopt allows multiple short option characters, each Descriptor can have only a single long option name. If you have multiple long option names referring to the same option use separate Descriptors that have the same index and type. You may repeat short option characters in such an alias Descriptor but there's no need to.

Dummy Descriptors:

You can use dummy Descriptors with an empty string for both shortopt and longopt to add text to the usage that is not related to a specific option. See help. The first dummy Descriptor will be used for unknown options (see below).

Unknown Option Descriptor:

The first dummy Descriptor in the list of Descriptors, whose shortopt and longopt are both the empty string, will be used as the Descriptor for unknown options. An unknown option is a string in the argument vector that is not a lone minus '-' but starts with a minus character and does not match any Descriptor's shortopt or longopt. Note that the dummy descriptor's check_arg function will be called and its return value will be evaluated as usual. I.e. if it returns ARG_ILLEGAL the parsing will be aborted with Parser::error() ==true. if check_arg does not return ARG_ILLEGAL the descriptor's index will be used to pick the linked list into which to put the unknown option.

If there is no dummy descriptor, unknown options will be dropped silently.

5.7.2.5 const char* const xmem::Descriptor::shortopt

Each char in this string will be accepted as a short option character.

The string must not include the minus character '-' or you'll get undefined behaviour.

If this Descriptor should not have short option characters, use the empty string "". NULL is not permitted here! See longopt for more information.

5.7.2.6 const int xmem::Descriptor::type

Used to distinguish between options with the same index. See index for details.


It is recommended that you use an enum rather than a plain int to make your code more readable.

The documentation for this struct was generated from the following file:

src/include/optionparser.h

5.8 xmem::ExampleArg Class Reference

Inheritance diagram for xmem::ExampleArg:



Static Public Member Functions


- static void printError (const char *msg1, const Option &opt, const char *msg2)
- static ArgStatus Unknown (const Option &option, bool msg)
- static ArgStatus Required (const Option & option, bool msg)
- static ArgStatus NonEmpty (const Option & option, bool msg)

The documentation for this class was generated from the following file:

src/include/ExampleArg.h

5.9 xmem::PrintUsageImplementation::FunctionWriter< Function > Struct Template Reference

Inheritance diagram for xmem::PrintUsageImplementation::FunctionWriter< Function >:



Public Member Functions

- virtual void operator() (const char *str, int size)
 Writes the given number of chars beginning at the given pointer somewhere.
- FunctionWriter (Function *w)

Public Attributes

• Function * write

The documentation for this struct was generated from the following file:

· src/include/optionparser.h

5.10 xmem::PrintUsageImplementation::IStringWriter Struct Reference

Inheritance diagram for xmem::PrintUsageImplementation::IStringWriter:

```
unern: Print Usge Englescentation: Straig Wase

unern: Print Usge Englescentation: Straig Wase

unern: Print Usge Englescentation: Straig Wase

unern: Print Usge Englescentation: Straig Wase - Francisco Straig Waser - Fra
```

Public Member Functions

virtual void operator() (const char *, int)
 Writes the given number of chars beginning at the given pointer somewhere.

The documentation for this struct was generated from the following file:


src/include/optionparser.h

5.11 xmem::LatencyBenchmark Class Reference

A type of benchmark that measures memory latency via random pointer chasing. Loading may be provided with separate threads which access memory as quickly as possible using given access patterns.

```
#include <LatencyBenchmark.h>
```

Inheritance diagram for xmem::LatencyBenchmark:



Public Member Functions

LatencyBenchmark (void *mem_array, size_t len, uint32_t iterations, uint32_t num_worker_threads, uint32_t mem_node, uint32_t cpu_node, pattern_mode_t pattern_mode, rw_mode_t rw_mode, chunk_size_t chunk_size, int64_t stride_size, std::vector< PowerReader * > dram_power_readers, std::string name)

Constructor. Parameters are passed directly to the Benchmark constructor. See Benchmark class documentation for parameter semantics.

virtual ~LatencyBenchmark ()

Destructor.

double getLoadMetricOnIter (uint32_t iter) const

Get the average load throughput in MB/sec that was imposed on the latency measurement during the given iteration.

• double getAvgLoadMetric () const

Get the overall average load throughput in MB/sec that was imposed on the latency measurement.

· virtual void report benchmark info () const

Reports benchmark configuration details to the console.

virtual void report_results () const

Reports results to the console.

Protected Member Functions

• virtual bool run core ()

The core benchmark function.

Protected Attributes

- std::vector< double > loadMetricOnIter
- double _averageLoadMetric

5.11.1 Detailed Description

A type of benchmark that measures memory latency via random pointer chasing. Loading may be provided with separate threads which access memory as quickly as possible using given access patterns.

5.11.2 Member Function Documentation

5.11.2.1 bool LatencyBenchmark::_run_core() [protected], [virtual]

The core benchmark function.

Returns

True on success.

Implements xmem::Benchmark.

5.11.2.2 double LatencyBenchmark::getAvgLoadMetric () const

Get the overall average load throughput in MB/sec that was imposed on the latency measurement.

Returns

The average throughput in MB/sec.

5.11.2.3 double LatencyBenchmark::getLoadMetricOnlter (uint32_t iter) const

Get the average load throughput in MB/sec that was imposed on the latency measurement during the given iteration. iter The iteration of interest.

Returns

The average throughput in MB/sec.

5.11.3 Member Data Documentation

5.11.3.1 double xmem::LatencyBenchmark::_averageLoadMetric [protected]

The average load throughput in MB/sec that was imposed on the latency measurement.

5.11.3.2 std::vector<**double**> **xmem::LatencyBenchmark::_loadMetricOnlter** [protected]

Load metrics for each iteration of the benchmark. This is in MB/s.

The documentation for this class was generated from the following files:


- src/include/LatencyBenchmark.h
- src/LatencyBenchmark.cpp

5.12 xmem::LatencyWorker Class Reference

Multithreading-friendly class to do memory loading.

#include <LatencyWorker.h>

Inheritance diagram for xmem::LatencyWorker:



Public Member Functions

 LatencyWorker (void *mem_array, size_t len, RandomFunction kernel_fptr, RandomFunction kernel_dummy-_fptr, int32_t cpu_affinity)

Constructor for sequential-access patterns.

virtual ~LatencyWorker ()

Destructor.

• virtual void run ()

Thread-safe worker method.

Additional Inherited Members

5.12.1 Detailed Description

Multithreading-friendly class to do memory loading.

5.12.2 Constructor & Destructor Documentation

5.12.2.1 LatencyWorker::LatencyWorker (void * mem_array, size_t len, RandomFunction kernel_fptr, RandomFunction kernel_dummy_fptr, int32_t cpu_affinity)

Constructor for sequential-access patterns.

Parameters

mem_array	Pointer to the memory region to use by this worker.
len	Length of the memory region to use by this worker.
kernel_fptr	Pointer to the sequential core benchmark kernel to use.
kernel_dummy	Pointer to the sequential dummy version of the core benchmark kernel to use.
fptr	
cpu_affinity	Logical CPU identifier to lock this worker's thread to.

The documentation for this class was generated from the following files:

- src/include/LatencyWorker.h
- src/LatencyWorker.cpp

5.13 xmem::PrintUsageImplementation::LinePartIterator Class Reference

Public Member Functions

· LinePartIterator (const Descriptor usage[])

Creates an iterator for usage.

bool nextTable ()

Moves iteration to the next table (if any). Has to be called once on a new LinePartIterator to move to the 1st table.

void restartTable ()

Reset iteration to the beginning of the current table.

bool nextRow ()

Moves iteration to the next row (if any). Has to be called once after each call to nextTable() to move to the 1st row of the table.

· void restartRow ()

Reset iteration to the beginning of the current row.

bool next ()

Moves iteration to the next part (if any). Has to be called once after each call to nextRow() to move to the 1st part of the row.

• int column ()

Returns the index (counting from 0) of the column in which the part pointed to by data() is located.

• int line ()

Returns the index (counting from 0) of the line within the current column this part belongs to.

• int length ()

Returns the length of the part pointed to by data() in raw chars (not UTF-8 characters).

int screenLength ()

Returns the width in screen columns of the part pointed to by data(). Takes multi-byte UTF-8 sequences and wide characters into account.

const char * data ()

Returns the current part of the iteration.

5.13.1 Member Function Documentation

5.13.1.1 bool xmem::PrintUsageImplementation::LinePartIterator::next() [inline]

Moves iteration to the next part (if any). Has to be called once after each call to nextRow() to move to the 1st part of the row.

Return values

false	if moving to next part failed because no further part exists.

See LinePartIterator for details about the iteration.

5.13.1.2 bool xmem::PrintUsageImplementation::LinePartIterator::nextRow() [inline]

Moves iteration to the next row (if any). Has to be called once after each call to nextTable() to move to the 1st row of the table.

Return values

Return values

false if moving to next row failed because no further row exists.

5.13.1.3 bool xmem::PrintUsageImplementation::LinePartIterator::nextTable() [inline]

Moves iteration to the next table (if any). Has to be called once on a new LinePartIterator to move to the 1st table.

false | if moving to next table failed because no further table exists.

The documentation for this class was generated from the following file:

• src/include/optionparser.h

5.14 xmem::PrintUsageImplementation::LineWrapper Class Reference

Public Member Functions

void flush (IStringWriter &write)

Writes out all remaining data from the LineWrapper using write. Unlike process() this method indents all lines including the first and will output a \n at the end (but only if something has been written).

void process (IStringWriter &write, const char *data, int len)

Process, wrap and output the next piece of data.

LineWrapper (int x1, int x2)

Constructs a LineWrapper that wraps its output to fit into screen columns x1 (incl.) to x2 (excl.).

5.14.1 Constructor & Destructor Documentation

5.14.1.1 xmem::PrintUsageImplementation::LineWrapper::LineWrapper (int x1, int x2) [inline]

Constructs a LineWrapper that wraps its output to fit into screen columns x1 (incl.) to x2 (excl.).

x1 gives the indentation LineWrapper uses if it needs to indent.

5.14.2 Member Function Documentation

5.14.2.1 void xmem::PrintUsageImplementation::LineWrapper::process (IStringWriter & write, const char * data, int len) [inline]

Process, wrap and output the next piece of data.

process() will output at least one line of output. This is not necessarily the data passed in. It may be data queued from a prior call to process(). If the internal buffer is full, more than 1 line will be output.

process() assumes that the a proper amount of indentation has already been output. It won't write any further indentation before the 1st line. If more than 1 line is written due to buffer constraints, the lines following the first will be indented by this method, though.

No \n is written by this method after the last line that is written.

Parameters

write	where to write the data.
data	the new chunk of data to write.
len	the length of the chunk of data to write.

The documentation for this class was generated from the following file:


• src/include/optionparser.h

5.15 xmem::LoadWorker Class Reference

Multithreading-friendly class to do memory loading.

#include <LoadWorker.h>

Inheritance diagram for xmem::LoadWorker:



Public Member Functions

• LoadWorker (void *mem_array, size_t len, SequentialFunction kernel_fptr, SequentialFunction kernel_tummy_fptr, int32_t cpu_affinity)

Constructor for sequential-access patterns.

• LoadWorker (void *mem_array, size_t len, RandomFunction kernel_fptr, RandomFunction kernel_dummy_fptr, int32_t cpu_affinity)

Constructor for random-access patterns.

virtual ~LoadWorker ()

Destructor.

• virtual void run ()

Thread-safe worker method.

Additional Inherited Members

5.15.1 Detailed Description

Multithreading-friendly class to do memory loading.

5.15.2 Constructor & Destructor Documentation

5.15.2.1 LoadWorker::LoadWorker (void * mem_array, size_t len, SequentialFunction kernel_fptr, SequentialFunction kernel_dummy_fptr, int32_t cpu_affinity)

Constructor for sequential-access patterns.

Parameters

mem_array	Pointer to the memory region to use by this worker.
len	Length of the memory region to use by this worker.
kernel_fptr	Pointer to the sequential core benchmark kernel to use.
kernel_dummy	Pointer to the sequential dummy version of the core benchmark kernel to use.
fptr	
cpu_affinity	Logical CPU identifier to lock this worker's thread to.

5.15.2.2 LoadWorker::LoadWorker (void * mem_array, size_t len, RandomFunction kernel_fptr, RandomFunction kernel_dummy_fptr, int32_t cpu_affinity)

Constructor for random-access patterns.

Parameters

mem_array	Pointer to the memory region to use by this worker.
len	Length of the memory region to use by this worker.
kernel_fptr	Pointer to the random core benchmark kernel to use.
kernel_dummy	Pointer to the random dummy version of the core benchmark kernel to use.
fptr	
cpu_affinity	Logical CPU identifier to lock this worker's thread to.

The documentation for this class was generated from the following files:


- src/include/LoadWorker.h
- src/LoadWorker.cpp

5.16 xmem::MemoryWorker Class Reference

Multithreading-friendly class to run memory access kernels.

#include <MemoryWorker.h>

Inheritance diagram for xmem::MemoryWorker:



Public Member Functions

• MemoryWorker (void *mem_array, size_t len, int32_t cpu_affinity)

Constructor

virtual ∼MemoryWorker ()

Destructor.

• virtual void run ()=0

Thread-safe worker method.

size_t getLen ()

Gets the length of the memory region used by this worker.

• uint64_t getBytesPerPass ()

Gets the number of bytes used in each pass of the benchmark by this worker.

• uint64_t getPasses ()

Gets the number of passes for this worker.

uint64 t getElapsedTicks ()

Gets the elapsed ticks for this worker on the core benchmark kernel.

• uint64_t getElapsedDummyTicks ()

Gets the elapsed ticks for this worker on the dummy version of the core benchmark kernel.

uint64_t getAdjustedTicks ()

Gets the adjusted ticks for this worker. This is elapsed ticks minus elapsed dummy ticks.

• bool hadWarning ()

Indicates whether worker's results may be questionable/inaccurate/invalid.

Protected Attributes

- void * _mem_array
- size t len
- int32_t _cpu_affinity
- uint64_t _bytes_per_pass
- uint64_t _passes
- uint64_t _elapsed_ticks
- uint64_t _elapsed_dummy_ticks
- uint64_t _adjusted_ticks
- · bool _warning
- bool _completed

Additional Inherited Members

5.16.1 Detailed Description

Multithreading-friendly class to run memory access kernels.

5.16.2 Constructor & Destructor Documentation

5.16.2.1 MemoryWorker::MemoryWorker (void * mem_array, size_t len, int32_t cpu_affinity)

Constructor.

Parameters

mem_	array	Pointer to the memory region to use by this worker.
	len	Length of the memory region to use by this worker.
passes_	per	for size-based benchmarking, this is the number of passes to execute in a single benchmark
itei	ration	iteration.
cpu_a	ffinity	Logical CPU identifier to lock this worker's thread to.

5.16.3 Member Function Documentation

5.16.3.1 uint64_t MemoryWorker::getAdjustedTicks ()

Gets the adjusted ticks for this worker. This is elapsed ticks minus elapsed dummy ticks.

Returns

The adjusted ticks for this worker.

5.16.3.2 uint64_t MemoryWorker::getBytesPerPass ()

Gets the number of bytes used in each pass of the benchmark by this worker.

Returns

Number of bytes in each pass.

```
5.16.3.3 uint64_t MemoryWorker::getElapsedDummyTicks ( )
Gets the elapsed ticks for this worker on the dummy version of the core benchmark kernel.
Returns
     The number of elapsed dummy ticks.
5.16.3.4 uint64_t MemoryWorker::getElapsedTicks ( )
Gets the elapsed ticks for this worker on the core benchmark kernel.
Returns
     The number of elapsed ticks.
5.16.3.5 size_t MemoryWorker::getLen()
Gets the length of the memory region used by this worker.
Returns
     Length of memory region in bytes.
5.16.3.6 uint64_t MemoryWorker::getPasses ( )
Gets the number of passes for this worker.
Returns
     The number of passes.
5.16.3.7 bool MemoryWorker::hadWarning ( )
Indicates whether worker's results may be questionable/inaccurate/invalid.
Returns
     True if the worker's results had a warning.
5.16.4 Member Data Documentation
5.16.4.1 uint64_t xmem::MemoryWorker::_adjusted_ticks [protected]
Elapsed ticks minus dummy elapsed ticks.
5.16.4.2 uint64_t xmem::MemoryWorker::_bytes_per_pass [protected]
Number of bytes accessed in each kernel pass.
5.16.4.3 bool xmem::MemoryWorker::_completed [protected]
```

If true, worker completed.

5.16.4.4 int32_t xmem::MemoryWorker::_cpu_affinity [protected]

The logical CPU affinity for this worker.

5.16.4.5 uint64_t xmem::MemoryWorker::_elapsed_dummy_ticks [protected]

Total elapsed ticks on the dummy kernel routine.

5.16.4.6 uint64_t xmem::MemoryWorker::_elapsed_ticks [protected]

Total elapsed ticks on the kernel routine.

5.16.4.7 size_t xmem::MemoryWorker::_len [protected]

The length of the memory region for this worker.

5.16.4.8 void* xmem::MemoryWorker::_mem_array [protected]

The memory region for this worker.

5.16.4.9 uint64_t xmem::MemoryWorker::_passes [protected]

Number of passes.

5.16.4.10 bool xmem::MemoryWorker::_warning [protected]


If true, results may be suspect.

The documentation for this class was generated from the following files:

- src/include/MemoryWorker.h
- src/MemoryWorker.cpp

5.17 xmem::MyArg Class Reference

Inheritance diagram for xmem::MyArg:



Static Public Member Functions

- static ArgStatus Integer (const Option & option, bool msg)
 Checks an option that it is an integer.
- static ArgStatus NonnegativeInteger (const Option & option, bool msg)

Checks an option that it is a nonnegative integer.

static ArgStatus PositiveInteger (const Option &option, bool msg)

Checks an option that it is a positive integer.

The documentation for this class was generated from the following file:

src/include/MyArg.h

5.18 xmem::Option Class Reference

A parsed option from the command line together with its argument if it has one.

```
#include <optionparser.h>
```

Public Member Functions

· int type () const

Returns Descriptor::type of this Option's Descriptor, or 0 if this Option is invalid (unused).

• int index () const

Returns Descriptor::index of this Option's Descriptor, or -1 if this Option is invalid (unused).

• int count ()

Returns the number of times this Option (or others with the same Descriptor::index) occurs in the argument vector.

· bool isFirst () const

Returns true iff this is the first element of the linked list.

• bool isLast () const

Returns true iff this is the last element of the linked list.

Option * first ()

Returns a pointer to the first element of the linked list.

Option * last ()

Returns a pointer to the last element of the linked list.

• Option * prev ()

Returns a pointer to the previous element of the linked list or NULL if called on first().

Option * prevwrap ()

Returns a pointer to the previous element of the linked list with wrap-around from first() to last().

• Option * next ()

Returns a pointer to the next element of the linked list or NULL if called on last().

Option * nextwrap ()

Returns a pointer to the next element of the linked list with wrap-around from last() to first().

void append (Option *new_last)

Makes new_last the new last() by chaining it into the list after last().

• operator const Option * () const

Casts from Option to const Option* but only if this Option is valid.

operator Option * ()

Casts from Option to Option* but only if this Option is valid.

• Option ()

Creates a new Option that is a one-element linked list and has NULL desc, name, arg and namelen.

Option (const Descriptor *desc_, const char *name_, const char *arg_)

Creates a new Option that is a one-element linked list and has the given values for desc, name and arg.

void operator= (const Option &orig)

Makes *this a copy of orig except for the linked list pointers.

• Option (const Option &orig)

Makes *this a copy of orig except for the linked list pointers.

Public Attributes

• const Descriptor * desc

Pointer to this Option's Descriptor.

• const char * name

The name of the option as used on the command line.

· const char * arg

Pointer to this Option's argument (if any).

· int namelen

The length of the option name.

5.18.1 Detailed Description

A parsed option from the command line together with its argument if it has one.

The Parser chains all parsed options with the same Descriptor::index together to form a linked list. This allows you to easily implement all of the common ways of handling repeated options and enable/disable pairs.

• Test for presence of a switch in the argument vector:

```
if ( options[QUIET] ) ...
```

• Evaluate –enable-foo/–disable-foo pair where the last one used wins:

```
if ( options[FOO].last()->type() == DISABLE ) ...
```

• Cumulative option (-v verbose, -vv more verbose, -vvv even more verbose):

```
int verbosity = options[VERBOSE].count();
```

Iterate over all –file=<fname> arguments:

```
for (Option* opt = options[FILE]; opt; opt = opt->next())
fname = opt->arg; ...
```

5.18.2 Constructor & Destructor Documentation

```
5.18.2.1 xmem::Option:Option (const Descriptor * desc_, const char * name_, const char * arg_ ) [inline]
```

Creates a new Option that is a one-element linked list and has the given values for desc, name and arg.

If name_points at a character other than '-' it will be assumed to refer to a short option and namelen will be set to 1. Otherwise the length will extend to the first '=' character or the string's 0-terminator.

```
5.18.2.2 xmem::Option:Option (const Option & orig) [inline]
```

Makes *this a copy of orig except for the linked list pointers.

After this operation *this will be a one-element linked list.

5.18.3 Member Function Documentation

```
5.18.3.1 void xmem::Option::append (Option * new_last ) [inline]
```

Makes new_last the new last() by chaining it into the list after last().

It doesn't matter which element you call append() on. The new element will always be appended to last().

Attention

new_last must not yet be part of a list, or that list will become corrupted, because this method does not unchain new last from an existing list.

```
5.18.3.2 int xmem::Option::count() [inline]
```

Returns the number of times this Option (or others with the same Descriptor::index) occurs in the argument vector.

This corresponds to the number of elements in the linked list this Option is part of. It doesn't matter on which element you call count(). The return value is always the same.

Use this to implement cumulative options, such as -v, -vv, -vvv for different verbosity levels.

Returns 0 when called for an unused/invalid option.

```
5.18.3.3 Option* xmem::Option::first() [inline]
```

Returns a pointer to the first element of the linked list.

Use this when you want the first occurrence of an option on the command line to take precedence. Note that this is not the way most programs handle options. You should probably be using last() instead.

Note

This method may be called on an unused/invalid option and will return a pointer to the option itself.

```
5.18.3.4 bool xmem::Option::isFirst() const [inline]
```

Returns true iff this is the first element of the linked list.

The first element in the linked list is the first option on the command line that has the respective Descriptor::index value.

Returns true for an unused/invalid option.

```
5.18.3.5 bool xmem::Option::isLast() const [inline]
```

Returns true iff this is the last element of the linked list.

The last element in the linked list is the last option on the command line that has the respective Descriptor::index value.

Returns true for an unused/invalid option.

```
5.18.3.6 Option* xmem::Option::last() [inline]
```

Returns a pointer to the last element of the linked list.

Use this when you want the last occurrence of an option on the command line to take precedence. This is the most common way of handling conflicting options.

Note

This method may be called on an unused/invalid option and will return a pointer to the option itself.

Tip:

If you have options with opposite meanings (e.g. -enable-foo and -disable-foo), you can assign them the same Descriptor::index to get them into the same list. Distinguish them by Descriptor::type and all you have to do is check last () ->type () to get the state listed last on the command line.

```
5.18.3.7 Option* xmem::Option::next() [inline]
```

Returns a pointer to the next element of the linked list or NULL if called on last().

If called on last() this method returns NULL. Otherwise it will return the option with the same Descriptor::index that follows this option on the command line.

```
5.18.3.8 Option* xmem::Option::nextwrap() [inline]
```

Returns a pointer to the next element of the linked list with wrap-around from last() to first().

If called on last() this method returns first(). Otherwise it will return the option with the same Descriptor::index that follows this option on the command line.

```
5.18.3.9 xmem::Option::operator const Option * ( ) const [inline]
```

Casts from Option to const Option* but only if this Option is valid.

If this Option is valid (i.e. desc!=NULL), returns this. Otherwise returns NULL. This allows testing an Option directly in an if-clause to see if it is used:

```
if (options[CREATE])
{
    ...
```

It also allows you to write loops like this:

```
for (Option* opt = options[FILE]; opt; opt = opt->next())
fname = opt->arg; ...
```

```
5.18.3.10 xmem::Option::operator Option * ( ) [inline]
```

Casts from Option to Option* but only if this Option is valid.

If this Option is valid (i.e. desc!=NULL), returns this. Otherwise returns NULL. This allows testing an Option directly in an if-clause to see if it is used:

```
if (options[CREATE])
{
    ...
}
```

It also allows you to write loops like this:

```
for (Option* opt = options[FILE]; opt; opt = opt->next())
fname = opt->arg; ...
```

```
5.18.3.11 void xmem::Option::operator= ( const Option & orig ) [inline]
```

Makes *this a copy of orig except for the linked list pointers.

After this operation *this will be a one-element linked list.

```
5.18.3.12 Option* xmem::Option::prev() [inline]
```

Returns a pointer to the previous element of the linked list or NULL if called on first().

If called on first() this method returns NULL. Otherwise it will return the option with the same Descriptor::index that precedes this option on the command line.

```
5.18.3.13 Option* xmem::Option::prevwrap() [inline]
```

Returns a pointer to the previous element of the linked list with wrap-around from first() to last().

If called on first() this method returns last(). Otherwise it will return the option with the same Descriptor::index that precedes this option on the command line.

```
5.18.3.14 int xmem::Option::type() const [inline]
```

Returns Descriptor::type of this Option's Descriptor, or 0 if this Option is invalid (unused).

Because this method (and last(), too) can be used even on unused Options with desc==0, you can (provided you arrange your types properly) switch on type() without testing validity first.

5.18.4 Member Data Documentation

```
5.18.4.1 const char* xmem::Option::arg
```

Pointer to this Option's argument (if any).

NULL if this option has no argument. Do not confuse this with the empty string which is a valid argument.

```
5.18.4.2 const Descriptor* xmem::Option::desc
```

Pointer to this Option's Descriptor.

Remember that the first dummy descriptor (see Descriptor::longopt) is used for unknown options.

Attention

desc==NULL signals that this Option is unused. This is the default state of elements in the result array. You don't need to test desc explicitly. You can simply write something like this:

```
if (options[CREATE])
{
    ...
}
```

This works because of operator const Option*() .

5.18.4.3 const char* xmem::Option::name

The name of the option as used on the command line.

The main purpose of this string is to be presented to the user in messages.

In the case of a long option, this is the actual argv pointer, i.e. the first character is a '-'. In the case of a short option this points to the option character within the argv string.

Note that in the case of a short option group or an attached option argument, this string will contain additional characters following the actual name. Use namelen to filter out the actual option name only.

5.18.4.4 int xmem::Option::namelen

The length of the option name.

Because name points into the actual argv string, the option name may be followed by more characters (e.g. other short options in the same short option group). This value is the number of bytes (not characters!) that are part of the actual name.

For a short option, this length is always 1. For a long option this length is always at least 2 if single minus long options are permitted and at least 3 if they are disabled.

Note


In the pathological case of a minus within a short option group (e.g. -xf-z), this length is incorrect, because this case will be misinterpreted as a long option and the name will therefore extend to the string's 0-terminator or a following '=" character if there is one. This is irrelevant for most uses of name and namelen. If you really need to distinguish the case of a long and a short option, compare name to the argv pointers. A long option's name is always identical to one of them, whereas a short option's is never.

The documentation for this class was generated from the following file:

• src/include/optionparser.h

5.19 xmem::PrintUsageImplementation::OStreamWriter< OStream > Struct Template Reference

Inheritance diagram for xmem::PrintUsageImplementation::OStreamWriter< OStream >:



Public Member Functions

virtual void operator() (const char *str, int size)

Writes the given number of chars beginning at the given pointer somewhere.

OStreamWriter (OStream &o)

Public Attributes

· OStream & ostream

The documentation for this struct was generated from the following file:

· src/include/optionparser.h

5.20 xmem::Parser Class Reference

Checks argument vectors for validity and parses them into data structures that are easier to work with.

```
#include <optionparser.h>
```

Classes

- struct Action
- class StoreOptionAction

Public Member Functions

• Parser ()

Creates a new Parser.

Parser (bool gnu, const Descriptor usage[], int argc, const char **argv, Option options[], Option buffer[], int min_abbr_len=0, bool single_minus_longopt=false, int bufmax=-1)

Creates a new Parser and immediately parses the given argument vector.

Parser (bool gnu, const Descriptor usage[], int argc, char **argv, Option options[], Option buffer[], int min_abbr_len=0, bool single_minus_longopt=false, int bufmax=-1)

Parser(...) with non-const argv.

Parser (const Descriptor usage[], int argc, const char **argv, Option options[], Option buffer[], int min_abbr_len=0, bool single_minus_longopt=false, int bufmax=-1)

```
POSIX Parser(...) (gnu==false).
```

• Parser (const Descriptor usage[], int argc, char **argv, Option options[], Option buffer[], int min_abbr_len=0, bool single_minus_longopt=false, int bufmax=-1)

POSIX Parser(...) (gnu==false) with non-const argv.

• void parse (bool gnu, const Descriptor usage[], int argc, const char **argv, Option options[], Option buffer[], int min_abbr_len=0, bool single_minus_longopt=false, int bufmax=-1)

Parses the given argument vector.

• void parse (bool gnu, const Descriptor usage[], int argc, char **argv, Option options[], Option buffer[], int min_abbr_len=0, bool single_minus_longopt=false, int bufmax=-1)

parse() with non-const argv.

• void parse (const Descriptor usage[], int argc, const char **argv, Option options[], Option buffer[], int min_abbr len=0, bool single minus longopt=false, int bufmax=-1)

POSIX parse() (gnu==false).

• void parse (const Descriptor usage[], int argc, char **argv, Option options[], Option buffer[], int min_abbr_- len=0, bool single minus longopt=false, int bufmax=-1)

POSIX parse() (gnu==false) with non-const argv.

• int optionsCount ()

Returns the number of valid Option objects in buffer[].

int nonOptionsCount ()

Returns the number of non-option arguments that remained at the end of the most recent parse() that actually encountered non-option arguments.

```
    const char ** nonOptions ()
```

Returns a pointer to an array of non-option arguments (only valid if nonOptionsCount() > 0).

• const char * nonOption (int i)

Returns nonOptions () [i] (without checking if i is in range!).

• bool error ()

Returns true if an unrecoverable error occurred while parsing options.

Friends

· struct Stats

5.20.1 Detailed Description

Checks argument vectors for validity and parses them into data structures that are easier to work with.

Example:

```
int main(int argc, char* argv[])
{
  argc-=(argc>0);    argv+=(argc>0);    // skip program name argv[0] if present
  option::Stats stats(usage, argc, argv);
  option::Option options[stats.options_max], buffer[stats.buffer_max];
  option::Parser parse(usage, argc, argv, options, buffer);

if (parse.error())
  return 1;

if (options[HELP])
...
```

5.20.2 Constructor & Destructor Documentation

5.20.2.1 xmem::Parser::Parser (bool gnu, const Descriptor usage[], int argc, const char ** argv, Option options[],

Option buffer[], int min_abbr_len = 0, bool single_minus_longopt = false, int bufmax = -1) [inline]

Creates a new Parser and immediately parses the given argument vector.

Parameters

gnu	if true, parse() will not stop at the first non-option argument. Instead it will reorder arguments so that all non-options are at the end. This is the default behaviour of GNU getopt() but is not conforming to POSIX.
	Note, that once the argument vector has been reordered, the gnu flag will have no further effect on this argument vector. So it is enough to pass gnu==true when creating Stats.
usage	Array of Descriptor objects that describe the options to support. The last entry of this array must have 0 in all fields.
argc	The number of elements from argv that are to be parsed. If you pass -1, the number will be determined automatically. In that case the argv list must end with a NULL pointer.
argv	The arguments to be parsed. If you pass -1 as argc the last pointer in the argv list must be NULL to mark the end.
options	Each entry is the first element of a linked list of Options. Each new option that is parsed will be appended to the list specified by that Option's Descriptor::index. If an entry is not yet used (i.e. the Option is invalid), it will be replaced rather than appended to. The minimum length of this array is the greatest Descriptor::index value that occurs in usage PLUS ONE.

buffer	Each argument that is successfully parsed (including unknown arguments, if they have a Descriptor whose CheckArg does not return ARG_ILLEGAL) will be stored in this array. parse() scans the array for the first invalid entry and begins writing at that index. You can pass bufmax to limit the number of options stored.
min_abbr_len	Passing a value min_abbr_len > 0 enables abbreviated long options. The parser will match a prefix of a long option as if it was the full long option (e.gfoob=10 will be interpreted as if it was -foobar=10), as long as the prefix has at least min_abbr_len characters (not counting the -) and is unambiguous. Be careful if combining min_abbr_len=1 with single_minus_longopt=true because the ambiguity check does not consider short options and abbreviated single minus long options will take precedence over short options.
single_minus longopt	Passing true for this option allows long options to begin with a single minus. The double minus form will still be recognized. Note that single minus long options take precedence over short options and short option groups. E.gfile would be interpreted as -file and not
bufmax	as -f -i -l -e (assuming a long option named "file" exists). The greatest index in the buffer[] array that parse() will write to is bufmax-1. If there are more options, they will be processed (in particular their CheckArg will be called) but not stored. If you used Stats::buffer_max to dimension this array, you can pass -1 (or not pass bufmax at all) which tells parse() that the buffer is "large enough".

Attention

Remember that options and buffer store Option objects, not pointers. Therefore it is not possible for the same object to be in both arrays. For those options that are found in both buffer[] and options[] the respective objects are independent copies. And only the objects in options[] are properly linked via Option::next() and Option::prev(). You can iterate over buffer[] to process all options in the order they appear in the argument vector, but if you want access to the other Options with the same Descriptor::index, then you must access the linked list via options[]. You can get the linked list in options from a buffer object via something like options[buffer[i].index()].

5.20.3 Member Function Documentation

```
5.20.3.1 bool xmem::Parser::error() [inline]
```

Returns ${\tt true}$ if an unrecoverable error occurred while parsing options.

An illegal argument to an option (i.e. CheckArg returns ARG_ILLEGAL) is an unrecoverable error that aborts the parse. Unknown options are only an error if their CheckArg function returns ARG_ILLEGAL. Otherwise they are collected. In that case if you want to exit the program if either an illegal argument or an unknown option has been passed, use code like this

```
if (parser.error() || options[UNKNOWN])
  exit(1):
```

5.20.3.2 const char** xmem::Parser::nonOptions() [inline]

Returns a pointer to an array of non-option arguments (only valid if nonOptionsCount () >0).

Note

- parse() does not copy arguments, so this pointer points into the actual argument vector as passed to parse().
- As explained at nonOptionsCount() this pointer is only changed by parse() calls that actually encounter non-option arguments. A parse() call that encounters only options, will not change nonOptions().

```
5.20.3.3 int xmem::Parser::nonOptionsCount() [inline]
```

Returns the number of non-option arguments that remained at the end of the most recent parse() that actually encountered non-option arguments.

Note

A parse() that does not encounter non-option arguments will leave this value as well as nonOptions() undisturbed. This means you can feed the Parser a default argument vector that contains non-option arguments (e.g. a default filename). Then you feed it the actual arguments from the user. If the user has supplied at least one non-option argument, all of the non-option arguments from the default disappear and are replaced by the user's non-option arguments. However, if the user does not supply any non-option arguments the defaults will still be in effect.

```
5.20.3.4 int xmem::Parser::optionsCount() [inline]
```

Returns the number of valid Option objects in buffer[].

Note

- The returned value always reflects the number of Options in the buffer[] array used for the most recent call to parse().
- The count (and the buffer[]) includes unknown options if they are collected (see Descriptor::longopt).

5.20.3.5 void xmem::Parser::parse (bool gnu, const Descriptor usage[], int argc, const char ** argv, Option options[],

Option buffer[], int min_abbr_len = 0, bool single_minus_longopt = false, int bufmax = -1) [inline]

Parses the given argument vector.

Parameters

gnu	if true, parse() will not stop at the first non-option argument. Instead it will reorder arguments so that all non-options are at the end. This is the default behaviour of GNU getopt() but is not conforming to POSIX.
	Note, that once the argument vector has been reordered, the gnu flag will have no further effect on this argument vector. So it is enough to pass gnu==true when creating Stats.
usage	Array of Descriptor objects that describe the options to support. The last entry of this array must have 0 in all fields.
argc	The number of elements from <code>argv</code> that are to be parsed. If you pass -1, the number will be determined automatically. In that case the <code>argv</code> list must end with a NULL pointer.
argv	The arguments to be parsed. If you pass -1 as argc the last pointer in the argv list must be NULL to mark the end.
options	Each entry is the first element of a linked list of Options. Each new option that is parsed will be appended to the list specified by that Option's Descriptor::index. If an entry is not yet used (i.e. the Option is invalid), it will be replaced rather than appended to. The minimum length of this array is the greatest Descriptor::index value that occurs in usage PLUS ONE.

buffer	Each argument that is successfully parsed (including unknown arguments, if they have a De-
	scriptor whose CheckArg does not return ARG_ILLEGAL) will be stored in this array. parse()
	scans the array for the first invalid entry and begins writing at that index. You can pass
	bufmax to limit the number of options stored.
min_abbr_len	Passing a value min_abbr_len > 0 enables abbreviated long options. The parser
	will match a prefix of a long option as if it was the full long option (e.gfoob=10 will be
	interpreted as if it was -foobar=10), as long as the prefix has at least min_abbr_len
	characters (not counting the -) and is unambiguous.
	Be careful if combining min_abbr_len=1 with single_minus_longopt=true be-
	cause the ambiguity check does not consider short options and abbreviated single minus
	long options will take precedence over short options.
single_minus	Passing true for this option allows long options to begin with a single minus. The double
longopt	minus form will still be recognized. Note that single minus long options take precedence over
	short options and short option groups. E.gfile would be interpreted as -file and not
	as -f -i -l -e (assuming a long option named "file" exists).
bufmax	The greatest index in the buffer[] array that parse() will write to is bufmax-1. If there
	are more options, they will be processed (in particular their CheckArg will be called) but not
	stored.
	If you used Stats::buffer_max to dimension this array, you can pass -1 (or not pass bufmax
	at all) which tells parse() that the buffer is "large enough".

Attention

Remember that options and buffer store Option objects, not pointers. Therefore it is not possible for the same object to be in both arrays. For those options that are found in both buffer[] and options[] the respective objects are independent copies. And only the objects in options[] are properly linked via Option::next() and Option::prev(). You can iterate over buffer[] to process all options in the order they appear in the argument vector, but if you want access to the other Options with the same Descriptor::index, then you must access the linked list via options[]. You can get the linked list in options from a buffer object via something like options[buffer[i].index()].

The documentation for this class was generated from the following file:


• src/include/optionparser.h

5.21 xmem::PowerReader Class Reference

An abstract base class for measuring power from an arbitrary source. This class is runnable using a worker thread.

#include <PowerReader.h>

Inheritance diagram for xmem::PowerReader:



Public Member Functions

- PowerReader (uint64_t sampling_period, double power_units, std::string name, int32_t cpu_affinity)
 Constructor.
- ∼PowerReader ()

Destructor.

• virtual void run ()=0

Starts measuring power at the rate implied by the sampling_period passed in the constructor. Call stop() to indicate to stop measuring.

• bool stop ()

Signals to stop measuring power. This is a non-blocking call and return does not indicate the measurement has actually stopped.

bool calculateMetrics ()

Calculates the relevant metrics.

• bool clear ()

Clears the stored power data.

• bool clear_and_reset ()

Clears the stored power data and resets state so that a new thread can be used with this object.

std::vector< double > getPowerTrace ()

Gets the power trace.

double getAveragePower ()

Gets the average power.

• double getPeakPower ()

Gets the peak power.

• double getLastSample ()

Gets the last sample.

uint64_t getSamplingPeriod ()

Gets the sampling period.

• double getPowerUnits ()

Gets the units of samples in watts.

• size_t getNumSamples ()

Gets the number of samples collected.

std::string name ()

Gets the name of this object.

Protected Attributes

- · bool _stop_signal
- · double power units
- std::string _name
- · int32_t _cpu_affinity
- std::vector< double > _power_trace
- double _average_power
- · double _peak_power
- size_t _num_samples
- · uint64_t _sampling_period

Additional Inherited Members

5.21.1 Detailed Description

An abstract base class for measuring power from an arbitrary source. This class is runnable using a worker thread.

5.21.2 Constructor & Destructor Documentation

5.21.2.1 PowerReader::PowerReader (uint64_t sampling_period, double power_units, std::string name, int32_t cpu_affinity)

Constructor.

Parameters

sampling_period	The time between power samples in milliseconds.
power_units	The power units for each sample in watts.
name	The human-friendly name of this object.
cpu_affinity	The logical CPU to be used by the thread calling this object's run() method. If negative, any
	CPU is OK (no affinity).



The last power sample measured.

```
5.21.3.6 size_t PowerReader::getNumSamples ( )
Gets the number of samples collected.
Returns
     Number of samples collected.
5.21.3.7 double PowerReader::getPeakPower ( )
Gets the peak power.
Returns
      The peak power sample from the measurements. If no data was collected, returns 0.
5.21.3.8 std::vector < double > PowerReader::getPowerTrace ( )
Gets the power trace.
Returns
     The measured power trace in a vector. If no data was collected, the vector will be empty.
5.21.3.9 double PowerReader::getPowerUnits ( )
Gets the units of samples in watts.
Returns
      The power units for each measurement sample in watts. For example, if each measurement is in milliwatts,
      then this returns 1e-3.
5.21.3.10 uint64_t PowerReader::getSamplingPeriod ( )
Gets the sampling period.
Returns
     The sampling period of the measurements in milliseconds.
5.21.3.11 std::string PowerReader::name ( )
Gets the name of this object.
Returns
```

The human-friendly name of this PowerReader.

```
5.21.3.12 bool PowerReader::stop ( )
```

Signals to stop measuring power. This is a non-blocking call and return does not indicate the measurement has actually stopped.

Returns

True if it successfully signaled a stop.

```
5.21.4 Member Data Documentation
```

```
5.21.4.1 double xmem::PowerReader::_average_power [protected]
```

The average power.

```
5.21.4.2 int32_t xmem::PowerReader::_cpu_affinity [protected]
```

CPU affinity for any thread using this object's run() method. If negative, no affinity preference.

```
5.21.4.3 std::string xmem::PowerReader::_name [protected]
```

Name of this object.

```
5.21.4.4 size_t xmem::PowerReader::_num_samples [protected]
```

The number of samples collected.

```
5.21.4.5 double xmem::PowerReader::_peak_power [protected]
```

The peak power observed.

```
5.21.4.6 std::vector<double> xmem::PowerReader::_power_trace [protected]
```

The time-ordered list of power samples. The first index is the oldest measurement.

```
5.21.4.7 double xmem::PowerReader::_power_units [protected]
```

Power units in watts.

```
5.21.4.8 uint64_t xmem::PowerReader::_sampling_period [protected]
```

Power sampling period in milliseconds.

```
5.21.4.9 bool xmem::PowerReader::_stop_signal [protected]
```

When true, the run() function should finish after the current sample iteration it is working on.

The documentation for this class was generated from the following files:

- src/include/PowerReader.h
- src/PowerReader.cpp

5.22 xmem::PrintUsageImplementation Struct Reference

Classes

- struct FunctionWriter
- · struct IStringWriter
- · class LinePartIterator
- · class LineWrapper
- struct OStreamWriter
- struct StreamWriter
- struct SyscallWriter
- · struct TemporaryWriter

Static Public Member Functions

- static void upmax (int &i1, int i2)
- static void **indent** (IStringWriter &write, int &x, int want_x)
- static bool isWideChar (unsigned ch)

Returns true if ch is the unicode code point of a wide character.

static void printUsage (IStringWriter &write, const Descriptor usage[], int width=80, int last_column_min_percent=50, int last_column_own_line_max_percent=75)

5.22.1 Member Function Documentation

```
5.22.1.1 static bool xmem::PrintUsageImplementation::isWideChar (unsigned ch) [inline], [static]
```

Returns true if ch is the unicode code point of a wide character.

Note

The following character ranges are treated as wide

```
1100..115F

2329..232A (just 2 characters!)

2E80..A4C6 except for 303F

A9600.A97C

AC00..D7FB

F900..FAFF

FE10..FE6B

FF01..FF60

FFE0..FFE6

1B000.....
```

The documentation for this struct was generated from the following file:


• src/include/optionparser.h

5.23 xmem::Runnable Class Reference

A base class for any object that implements a thread-safe run() function for use by Thread objects.

```
#include <Runnable.h>
```

Inheritance diagram for xmem::Runnable:



Public Member Functions

• Runnable ()

Constructor.

∼Runnable ()

Destructor.

• virtual void run ()=0

Does some "work". Pure virtual method that any derived class must implement in a thread-safe manner.

Protected Member Functions

bool <u>acquireLock</u> (int32_t timeout)

Acquires the object lock to access all object state in thread-safe manner.

• bool _releaseLock ()

Releases the object lock to access all object state in thread-safe manner.

5.23.1 Detailed Description

A base class for any object that implements a thread-safe run() function for use by Thread objects.

5.23.2 Member Function Documentation

5.23.2.1 bool Runnable::_acquireLock(int32_t timeout) [protected]

Acquires the object lock to access all object state in thread-safe manner.

Parameters

timeout	timeout in milliseconds to acquire the lock. If 0, does not wait at all. If negative, waits indefi-
	nitely.

Returns

true on success. If not successful, the lock was not acquired, possibly due to a timeout, or the lock might already be held.

5.23.2.2 bool Runnable::_releaseLock() [protected]

Releases the object lock to access all object state in thread-safe manner.

Returns

true on success. If not successful, the lock is either still held or the call was illegal (e.g., releasing a lock that was never acquired).

The documentation for this class was generated from the following files:

- · src/include/Runnable.h
- src/Runnable.cpp

5.24 xmem::Stats Struct Reference

Determines the minimum lengths of the buffer and options arrays used for Parser.

```
#include <optionparser.h>
```

Classes

class CountOptionsAction

Public Member Functions

• Stats ()

Creates a Stats object with counts set to 1 (for the sentinel element).

 Stats (bool gnu, const Descriptor usage[], int argc, const char **argv, int min_abbr_len=0, bool single_minus_ longopt=false)

Creates a new Stats object and immediately updates it for the given usage and argument vector. You may pass 0 for argc and/or argv, if you just want to update options_max.

• Stats (bool gnu, const Descriptor usage[], int argc, char **argv, int min_abbr_len=0, bool single_minus_longopt=false)

Stats(...) with non-const argv.

• Stats (const Descriptor usage[], int argc, const char **argv, int min_abbr_len=0, bool single_minus_longopt=false)

```
POSIX Stats(...) (gnu==false).
```

- Stats (const Descriptor usage[], int argc, char **argv, int min_abbr_len=0, bool single_minus_longopt=false)

 POSIX Stats(...) (gnu==false) with non-const argv.
- void add (bool gnu, const Descriptor usage[], int argc, const char **argv, int min_abbr_len=0, bool single_minus longopt=false)

Updates this Stats object for the given usage and argument vector. You may pass 0 for argc and/or argv, if you just want to update options max.

void add (bool gnu, const Descriptor usage[], int argc, char **argv, int min_abbr_len=0, bool single_minus_longopt=false)

add() with non-const argv.

void add (const Descriptor usage[], int argc, const char **argv, int min_abbr_len=0, bool single_minus_longopt=false)

POSIX add() (gnu==false).

void add (const Descriptor usage[], int argc, char **argv, int min_abbr_len=0, bool single_minus_longopt=false)

POSIX add() (gnu==false) with non-const argv.

Public Attributes

unsigned buffer_max

Number of elements needed for a buffer[] array to be used for parsing the same argument vectors that were fed into this Stats object.

· unsigned options_max

Number of elements needed for an options[] array to be used for parsing the same argument vectors that were fed into this Stats object.

5.24.1 Detailed Description

Determines the minimum lengths of the buffer and options arrays used for Parser.

Because Parser doesn't use dynamic memory its output arrays have to be pre-allocated. If you don't want to use fixed size arrays (which may turn out too small, causing command line arguments to be dropped), you can use Stats to determine the correct sizes. Stats work cumulative. You can first pass in your default options and then the real options and afterwards the counts will reflect the union.

5.24.2 Constructor & Destructor Documentation

5.24.2.1 xmem::Stats::Stats (bool gnu, const Descriptor usage[], int argc, const char ** argv, int min_abbr_len = 0, bool single_minus_longopt = false) [inline]

Creates a new Stats object and immediately updates it for the given usage and argument vector. You may pass 0 for argc and/or argv, if you just want to update options max.

Note

The calls to Stats methods must match the later calls to Parser methods. See Parser::parse() for the meaning of the arguments.

5.24.3 Member Function Documentation

5.24.3.1 void xmem::Stats::add (bool gnu, const Descriptor usage[], int argc, const char ** argv, int min_abbr_len = 0, bool single_minus_longopt = false) [inline]

Updates this Stats object for the given usage and argument vector. You may pass 0 for argc and/or argv, if you just want to update options_max.

Note

The calls to Stats methods must match the later calls to Parser methods. See Parser::parse() for the meaning of the arguments.

5.24.4 Member Data Documentation

5.24.4.1 unsigned xmem::Stats::buffer_max

Number of elements needed for a buffer[] array to be used for parsing the same argument vectors that were fed into this Stats object.

Note

This number is always 1 greater than the actual number needed, to give you a sentinel element.

5.24.4.2 unsigned xmem::Stats::options_max

Number of elements needed for an options[] array to be used for parsing the same argument vectors that were fed into this Stats object.

Note


- This number is always 1 greater than the actual number needed, to give you a sentinel element.
- This number depends only on the usage, not the argument vectors, because the options array needs exactly one slot for each possible Descriptor::index.

The documentation for this struct was generated from the following file:

• src/include/optionparser.h

5.25 xmem::Parser::StoreOptionAction Class Reference

Inheritance diagram for xmem::Parser::StoreOptionAction:



Public Member Functions

- StoreOptionAction (Parser &parser_, Option options_[], Option buffer_[], int bufmax_)
 Number of slots in buffer. -1 means "large enough".
- bool perform (Option &option)

Called by Parser::workhorse() for each Option that has been successfully parsed (including unknown options if they have a Descriptor whose Descriptor::check_arg does not return ARG_ILLEGAL.

bool finished (int numargs, const char **args)

Called by Parser::workhorse() after finishing the parse.

5.25.1 Constructor & Destructor Documentation

5.25.1.1 xmem::Parser::StoreOptionAction::StoreOptionAction (Parser & parser_, Option options_[], Option buffer_[], int bufmax_) [inline]

Number of slots in buffer. -1 means "large enough".

Creates a new StoreOption action.

Parameters

	parser_	the parser whose op_count should be updated.
	options_	each Option o is chained into the linked list options_[o.desc->index]
Ī	buffer_	each Option is appended to this array as long as there's a free slot.

5.25.2 Member Function Documentation

5.25.2.1 bool xmem::Parser::StoreOptionAction::finished (int numargs, const char ** args) [inline], [virtual]

Called by Parser::workhorse() after finishing the parse.

Parameters

numargs	the number of non-option arguments remaining
args	pointer to the first remaining non-option argument (if numargs $>$ 0).

Returns

false iff a fatal error has occurred.

Reimplemented from xmem::Parser::Action.

5.25.2.2 bool xmem::Parser::StoreOptionAction::perform(Option &) [inline], [virtual]

Called by Parser::workhorse() for each Option that has been successfully parsed (including unknown options if they have a Descriptor whose Descriptor::check_arg does not return ARG_ILLEGAL.

Returns false iff a fatal error has occured and the parse should be aborted.

Reimplemented from xmem::Parser::Action.

The documentation for this class was generated from the following file:

• src/include/optionparser.h

5.26 xmem::PrintUsageImplementation::StreamWriter< Function, Stream > Struct Template Reference

Inheritance diagram for xmem::PrintUsageImplementation::StreamWriter< Function, Stream >:

xmem::PrintUsageImplementation::IStringWriter

xmem::PrintUsageImplementation::StreamWriter< Function, Stream >

Public Member Functions

- virtual void operator() (const char *str, int size)
 Writes the given number of chars beginning at the given pointer somewhere.
- StreamWriter (Function *w, Stream *s)

Public Attributes

- Function * fwrite
- Stream * stream

The documentation for this struct was generated from the following file:

· src/include/optionparser.h

5.27 xmem::PrintUsageImplementation::SyscallWriter< Syscall > Struct Template Reference

Inheritance diagram for xmem::PrintUsageImplementation::SyscallWriter< Syscall >:



Public Member Functions

- virtual void operator() (const char *str, int size)
 Writes the given number of chars beginning at the given pointer somewhere.
- SyscallWriter (Syscall *w, int f)

Public Attributes


- Syscall * write
- int fd

The documentation for this struct was generated from the following file:

• src/include/optionparser.h

5.28 xmem::PrintUsageImplementation::TemporaryWriter< Temporary > Struct Template Reference

Inheritance diagram for xmem::PrintUsageImplementation::TemporaryWriter< Temporary >:



Public Member Functions

- virtual void operator() (const char *str, int size)
 Writes the given number of chars beginning at the given pointer somewhere.
- TemporaryWriter (const Temporary &u)

Public Attributes

· const Temporary & userstream

The documentation for this struct was generated from the following file:

· src/include/optionparser.h

5.29 xmem::Thread Class Reference

a nice wrapped thread interface independent of particular OS API

```
#include <Thread.h>
```

Public Member Functions

- Thread (Runnable *target)
- ∼Thread ()
- bool create_and_start ()
- bool join ()
- bool cancel ()
- int32_t getExitCode ()
- bool started ()
- bool completed ()
- bool validTarget ()
- · bool created ()
- bool isThreadSuspended ()
- bool isThreadRunning ()
- Runnable * getTarget ()

5.29.1 Detailed Description

a nice wrapped thread interface independent of particular OS API

5.29.2 Constructor & Destructor Documentation

```
5.29.2.1 Thread::Thread ( Runnable * target )
```

Constructor. Does not actually create the real thread or run it.

Parameters

target The target object to do some work with in a new thread.

```
5.29.2.2 Thread::\simThread ( )
```

Destructor. Immediately cancels the thread if it exists. This can be unsafe!

5.29.3 Member Function Documentation

```
5.29.3.1 bool Thread::cancel ( )
```

Cancels the worker thread immediately. This should only be done in emergencies, as it is effectively killed and undefined behavior might occur.

Returns

true if the worker thread was successfully killed.

```
5.29.3.2 bool Thread::completed ( )
```

Returns

true if the thread completed, regardless of the manner in which it terminated. Returns false if it has not been started.

```
5.29.3.3 bool Thread::create_and_start()
```

Creates and starts the thread immediately if the target Runnable is valid. This invokes the run() method in the Runnable target that was passed in the constructor.

Returns

true if the thread was successfully created and started.

```
5.29.3.4 bool Thread::created ( )
```

Returns

true if the thread has been created successfully.

```
5.29.3.5 int32_t Thread::getExitCode ( )
```

Returns

the exit code of the worker thread if it completed. If it did not complete or has not started, returns 0.

```
5.29.3.6 Runnable * Thread::getTarget ( )
```

Returns

a pointer to the target Runnable object

5.29.3.7 bool Thread::isThreadRunning ()

Returns

true if the thread is running. Returns false if the thread has not been created.

5.29.3.8 bool Thread::isThreadSuspended ()

Returns

true if the thread is suspended. Returns false if the thread has not been created.

```
5.29.3.9 bool Thread::join ( )
```

Blocks the calling thread until the worker thread managed by this object terminates. For simplicity, this does not support a timeout due to pthreads incompatibility with the Windows threading API. If the worker thread has already terminated, returns immediately. If the worker has not yet started, returns immediately.

Returns

true if the worker thread terminated successfully, false otherwise.

```
5.29.3.10 bool Thread::started ( )
```

Returns

true if the thread has been started, regardless if has completed or not.

```
5.29.3.11 bool Thread::validTarget ( )
```

Returns

true if the Runnable target is valid.

The documentation for this class was generated from the following files:


- src/include/Thread.h
- src/Thread.cpp

5.30 xmem::ThroughputBenchmark Class Reference

A type of benchmark that measures memory throughput.

```
#include <ThroughputBenchmark.h>
```

Inheritance diagram for xmem::ThroughputBenchmark:



Public Member Functions

• ThroughputBenchmark (void *mem_array, size_t len, uint32_t iterations, uint32_t num_worker_threads, uint32_t mem_node, uint32_t cpu_node, pattern_mode_t pattern_mode, rw_mode_t rw_mode, chunk_size_t chunk_size, int64_t stride_size, std::vector< PowerReader * > dram_power_readers, std::string name)

Constructor. Parameters are passed directly to the Benchmark constructor. See Benchmark class documentation for parameter semantics.

virtual ~ThroughputBenchmark ()

Destructor.

Protected Member Functions

virtual bool _run_core ()

The core benchmark function.

Additional Inherited Members

5.30.1 Detailed Description

A type of benchmark that measures memory throughput.

5.30.2 Member Function Documentation

```
5.30.2.1 bool ThroughputBenchmark::_run_core() [protected], [virtual]
```

The core benchmark function.

Returns

True on success.

Implements xmem::Benchmark.

The documentation for this class was generated from the following files:

- · src/include/ThroughputBenchmark.h
- src/ThroughputBenchmark.cpp

5.31 xmem::Timer Class Reference

This class abstracts some characteristics of simple high resolution stopwatch timer. However, due to the inability or complexity of abstracting shared hardware timers, this class does not actually provide start and stop functions.

```
#include <Timer.h>
```

Public Member Functions

• Timer ()

Constructor. This may take a noticeable amount of time.

• uint64_t get_ticks_per_sec ()

Gets ticks per second for this timer.

• double get_ns_per_tick ()

Gets nanoseconds per tick for this timer.

Protected Attributes

- uint64 t ticks per sec
- double _ns_per_tick

5.31.1 Detailed Description

This class abstracts some characteristics of simple high resolution stopwatch timer. However, due to the inability or complexity of abstracting shared hardware timers, this class does not actually provide start and stop functions.

5.31.2 Member Function Documentation

```
5.31.2.1 double Timer::get_ns_per_tick ( )
```

Gets nanoseconds per tick for this timer.

Returns

the number of nanoseconds per tick

```
5.31.2.2 uint64_t Timer::get_ticks_per_sec ( )
```

Gets ticks per second for this timer.

Returns

The reported number of ticks per second.

5.31.3 Member Data Documentation

```
5.31.3.1 double xmem::Timer::_ns_per_tick [protected]
```

Nanoseconds per tick for this timer.

```
5.31.3.2 uint64_t xmem::Timer::_ticks_per_sec [protected]
```

Ticks per second for this timer.

The documentation for this class was generated from the following files:

- src/include/Timer.h
- src/Timer.cpp

Chapter 6

File Documentation

6.1 src/Benchmark.cpp File Reference

Implementation file for the Benchmark class.

```
#include <Benchmark.h>
#include <common.h>
#include <benchmark_kernels.h>
#include <PowerReader.h>
#include <cstdint>
#include <iostream>
#include <vector>
#include <time.h>
```

6.1.1 Detailed Description

Implementation file for the Benchmark class.

6.2 src/benchmark_kernels.cpp File Reference

Implementation file for benchmark kernel functions for doing the actual work we care about. :)

```
#include <benchmark_kernels.h>
#include <common.h>
#include <iostream>
#include <random>
#include <algorithm>
#include <time.h>
```

6.2.1 Detailed Description

Implementation file for benchmark kernel functions for doing the actual work we care about. :) Optimization tricks include:

UNROLL macros to manual loop unrolling. This reduces the relative branch overhead of the loop. We don't
want to benchmark loops, we want to benchmark memory! But unrolling too much can hurt code size and
instruction locality, potentially decreasing I-cache utilization and causing extra overheads. This is why we
allow multiple unroll lengths at compile-time.

• volatile keyword to prevent compiler from optimizing the code and removing instructions that we need. The compiler is too smart for its own good!

6.3 src/BenchmarkManager.cpp File Reference

Implementation file for the BenchmarkManager class.

```
#include <BenchmarkManager.h>
#include <common.h>
#include <Configurator.h>
#include <cstdint>
#include <stdlib.h>
#include <iostream>
#include <sstream>
#include <assert.h>
```

6.3.1 Detailed Description

Implementation file for the BenchmarkManager class.

6.4 src/common.cpp File Reference

Implementation file for common preprocessor definitions, macros, functions, and global constants.

```
#include <common.h>
#include <Timer.h>
#include <iostream>
```

Variables

```
bool xmem::g_verbose = false
size_t xmem::g_page_size
size_t xmem::g_large_page_size
uint32_t xmem::g_num_nodes
uint32_t xmem::g_num_logical_cpus
uint32_t xmem::g_num_physical_cpus
uint32_t xmem::g_num_physical_packages
uint32_t xmem::g_total_l1_caches
uint32_t xmem::g_total_l2_caches
uint32_t xmem::g_total_l3_caches
uint32_t xmem::g_total_l4_caches
uint32_t xmem::g_starting_test_index
uint32_t xmem::g_test_index
uint64_t xmem::g_ticks_per_sec
double xmem::g_ns_per_tick
```

6.4.1 Detailed Description

Implementation file for common preprocessor definitions, macros, functions, and global constants.

6.5 src/Configurator.cpp File Reference

Implementation file for the Configurator class and some helper data structures.

```
#include <Configurator.h>
#include <common.h>
#include <optionparser.h>
#include <MyArg.h>
#include <cstdint>
#include <iostream>
#include <string>
```

6.5.1 Detailed Description

Implementation file for the Configurator class and some helper data structures.

6.6 src/ext/DelayInjectedLoadedLatencyBenchmark/delay_injected_benchmark_kernels.cpp File Reference

Implementation file for benchmark kernel functions for the delay-injected loaded latency benchmark.

```
#include <delay_injected_benchmark_kernels.h>
#include <common.h>
#include <iostream>
```

6.6.1 Detailed Description

Implementation file for benchmark kernel functions for the delay-injected loaded latency benchmark. Optimization tricks include:

- UNROLL macros to manual loop unrolling. This reduces the relative branch overhead of the loop. We don't want to benchmark loops, we want to benchmark memory! But unrolling too much can hurt code size and instruction locality, potentially decreasing I-cache utilization and causing extra overheads. This is why we allow multiple unroll lengths at compile-time.
- volatile keyword to prevent compiler from optimizing the code and removing instructions that we need. The compiler is too smart for its own good!

6.7 src/ext/DelayInjectedLoadedLatencyBenchmark/DelayInjectedLoadedLatencyBenchmark.cpp File Reference

 $Implementation \ file \ for \ the \ DelayInjected Latency Benchmark \ class.$

```
#include <common.h>
```

6.7.1 Detailed Description

Implementation file for the DelayInjectedLatencyBenchmark class.

6.8 src/include/Benchmark.h File Reference

Header file for the Benchmark class.

```
#include <common.h>
#include <PowerReader.h>
#include <Thread.h>
#include <Runnable.h>
#include <cstdint>
#include <string>
#include <vector>
```

Classes

· class xmem::Benchmark

Flexible abstract class for any memory benchmark.

6.8.1 Detailed Description

Header file for the Benchmark class.

6.9 src/include/benchmark kernels.h File Reference

Header file for benchmark kernel functions for doing the actual work we care about. :)

```
#include <common.h>
#include <cstdint>
#include <cstddef>
```

Typedefs

- typedef int32_t(* xmem::SequentialFunction)(void *, void *)
- typedef int32_t(* xmem::RandomFunction)(uintptr_t *, uintptr_t **, size_t)

Functions

bool xmem::determineSequentialKernel (rw_mode_t rw_mode, chunk_size_t chunk_size, int64_t stride_size, SequentialFunction *kernel_function, SequentialFunction *dummy_kernel_function)

Determines which sequential memory access kernel to use based on the read/write mode, chunk size, and stride size.

• bool xmem::determineRandomKernel (rw_mode_t rw_mode, chunk_size_t chunk_size, RandomFunction *kernel_function, RandomFunction *dummy_kernel_function)

Determines which random memory access kernel to use based on the read/write mode, chunk size, and stride size.

bool xmem::buildRandomPointerPermutation (void *start_address, void *end_address, chunk_size_t chunk_size)

Builds a random chain of pointers within the specified memory region.

int32_t xmem::dummy_chasePointers (uintptr_t *, uintptr_t **, size_t len)

Mimics the chasePointers() method but doesn't do the memory accesses.

• int32_t xmem::chasePointers (uintptr_t *first_address, uintptr_t **last_touched_address, size_t len)

Walks over the allocated memory in random order by chasing pointers.

int32_t xmem::dummy_empty (void *, void *)

Does nothing. Used for measuring the time it takes just to call a benchmark routine via function pointer.

• int32 t xmem::dummy forwSequentialLoop Word32 (void *start address, void *end address)

Used for measuring the time spent doing everything in forward sequential Word 32 loops except for the memory access itself.

int32_t xmem::dummy_forwSequentialLoop_Word64 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward sequential Word 64 loops except for the memory access itself.

int32_t xmem::dummy_forwSequentialLoop_Word128 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward sequential Word 128 loops except for the memory access itself.

int32_t xmem::dummy_forwSequentialLoop_Word256 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward sequential Word 256 loops except for the memory access itself.

• int32 t xmem::dummy revSequentialLoop Word32 (void *start address, void *end address)

Used for measuring the time spent doing everything in reverse sequential Word 32 loops except for the memory access itself.

• int32_t xmem::dummy_revSequentialLoop_Word64 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in reverse sequential Word 64 loops except for the memory access itself.

int32_t xmem::dummy_revSequentialLoop_Word128 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in reverse sequential Word 128 loops except for the memory access itself.

• int32 t xmem::dummy revSequentialLoop Word256 (void *start address, void *end address)

Used for measuring the time spent doing everything in reverse sequential Word 256 loops except for the memory access itself.

int32_t xmem::dummy_forwStride2Loop_Word32 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 2-strided Word 32 loops except for the memory access itself.

int32_t xmem::dummy_forwStride2Loop_Word64 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 2-strided Word 64 loops except for the memory access itself.

int32_t xmem::dummy_forwStride2Loop_Word128 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 2-strided Word 128 loops except for the memory access itself.

• int32_t xmem::dummy_forwStride2Loop_Word256 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 2-strided Word 256 loops except for the memory access itself.

• int32_t xmem::dummy_revStride2Loop_Word32 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in reverse 2-strided Word 32 loops except for the memory access itself

• int32 t xmem::dummy revStride2Loop Word64 (void *start address, void *end address)

Used for measuring the time spent doing everything in reverse 2-strided Word 64 loops except for the memory access itself

int32_t xmem::dummy_revStride2Loop_Word128 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in reverse 2-strided Word 128 loops except for the memory access itself.

int32_t xmem::dummy_revStride2Loop_Word256 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in reverse 2-strided Word 256 loops except for the memory access itself.

• int32_t xmem::dummy_forwStride4Loop_Word32 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 4-strided Word 32 loops except for the memory access itself.

• int32_t xmem::dummy_forwStride4Loop_Word64 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 4-strided Word 64 loops except for the memory access itself

int32_t xmem::dummy_forwStride4Loop_Word128 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 4-strided Word 128 loops except for the memory access itself.

int32_t xmem::dummy_forwStride4Loop_Word256 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 4-strided Word 256 loops except for the memory access itself.

int32_t xmem::dummy_revStride4Loop_Word32 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in reverse 4-strided Word 32 loops except for the memory access itself

• int32 t xmem::dummy revStride4Loop Word64 (void *start address, void *end address)

Used for measuring the time spent doing everything in reverse 4-strided Word 64 loops except for the memory access itself

• int32 t xmem::dummy revStride4Loop Word128 (void *start address, void *end address)

Used for measuring the time spent doing everything in reverse 4-strided Word 128 loops except for the memory access itself.

• int32 t xmem::dummy revStride4Loop Word256 (void *start address, void *end address)

Used for measuring the time spent doing everything in reverse 4-strided Word 256 loops except for the memory access itself.

int32_t xmem::dummy_forwStride8Loop_Word32 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 8-strided Word 32 loops except for the memory access itself.

• int32_t xmem::dummy_forwStride8Loop_Word64 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 8-strided Word 64 loops except for the memory access itself.

int32_t xmem::dummy_forwStride8Loop_Word128 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 8-strided Word 128 loops except for the memory access itself

• int32 t xmem::dummy forwStride8Loop Word256 (void *start address, void *end address)

Used for measuring the time spent doing everything in forward 8-strided Word 256 loops except for the memory access itself.

• int32 t xmem::dummy revStride8Loop Word32 (void *start address, void *end address)

Used for measuring the time spent doing everything in reverse 8-strided Word 32 loops except for the memory access itself.

• int32 t xmem::dummy revStride8Loop Word64 (void *start address, void *end address)

Used for measuring the time spent doing everything in reverse 8-strided Word 64 loops except for the memory access itself.

int32_t xmem::dummy_revStride8Loop_Word128 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in reverse 8-strided Word 128 loops except for the memory access itself.

int32_t xmem::dummy_revStride8Loop_Word256 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in reverse 8-strided Word 256 loops except for the memory access itself.

• int32_t xmem::dummy_forwStride16Loop_Word32 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 16-strided Word 32 loops except for the memory access itself.

int32_t xmem::dummy_forwStride16Loop_Word64 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 16-strided Word 64 loops except for the memory access itself.

• int32_t xmem::dummy_forwStride16Loop_Word128 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in forward 16-strided Word 128 loops except for the memory access itself.

• int32 t xmem::dummy forwStride16Loop Word256 (void *start address, void *end address)

Used for measuring the time spent doing everything in forward 16-strided Word 256 loops except for the memory access itself

int32_t xmem::dummy_revStride16Loop_Word32 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in reverse 16-strided Word 32 loops except for the memory access itself.

int32_t xmem::dummy_revStride16Loop_Word64 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in reverse 16-strided Word 64 loops except for the memory access itself.

int32_t xmem::dummy_revStride16Loop_Word128 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in reverse 16-strided Word 128 loops except for the memory access itself.

• int32 t xmem::dummy revStride16Loop Word256 (void *start address, void *end address)

Used for measuring the time spent doing everything in reverse 16-strided Word 256 loops except for the memory access itself

• int32_t xmem::dummy_randomLoop_Word64 (uintptr_t *, uintptr_t **, size_t len)

Mimics the randomRead Word64 and randomWrite Word64 functions except for the memory accesses.

• int32_t xmem::dummy_randomLoop_Word128 (uintptr_t *first_address, uintptr_t **last_touched_address, size_t len)

Mimics the randomRead_Word128 and randomWrite_Word128 functions except for the memory accesses.

• int32_t xmem::dummy_randomLoop_Word256 (uintptr_t *first_address, uintptr_t **last_touched_address, size t len)

Mimics the randomRead_Word256 and randomWrite_Word256 functions except for the memory accesses.

• int32_t xmem::forwSequentialRead_Word32 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 32-bit chunks.

• int32 t xmem::forwSequentialRead_Word64 (void *start address, void *end address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks.

int32_t xmem::forwSequentialRead_Word128 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 128-bit chunks.

int32_t xmem::forwSequentialRead_Word256 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 256-bit chunks.

• int32 t xmem::revSequentialRead Word32 (void *start address, void *end address)

Walks over the allocated memory reverse sequentially, reading in 32-bit chunks.

int32_t xmem::revSequentialRead_Word64 (void *start_address, void *end_address)

Walks over the allocated memory reverse sequentially, reading in 64-bit chunks.

int32_t xmem::revSequentialRead_Word128 (void *start_address, void *end_address)

Walks over the allocated memory reverse sequentially, reading in 128-bit chunks.

• int32 t xmem::revSequentialRead_Word256 (void *start address, void *end address)

Walks over the allocated memory reverse sequentially, reading in 256-bit chunks.

int32_t xmem::forwSequentialWrite_Word32 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, writing in 32-bit chunks.

• int32_t xmem::forwSequentialWrite_Word64 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, writing in 64-bit chunks.

• int32 t xmem::forwSequentialWrite_Word128 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, writing in 128-bit chunks.

• int32 t xmem::forwSequentialWrite Word256 (void *start address, void *end address)

Walks over the allocated memory forward sequentially, writing in 256-bit chunks.

• int32 t xmem::revSequentialWrite Word32 (void *start address, void *end address)

Walks over the allocated memory reverse sequentially, writing in 32-bit chunks.

int32 t xmem::revSequentialWrite Word64 (void *start address, void *end address)

Walks over the allocated memory reverse sequentially, writing in 64-bit chunks.

• int32 t xmem::revSequentialWrite Word128 (void *start address, void *end address)

Walks over the allocated memory reverse sequentially, writing in 128-bit chunks.

• int32_t xmem::revSequentialWrite_Word256 (void *start_address, void *end_address)

Walks over the allocated memory reverse sequentially, writing in 256-bit chunks.

- int32_t xmem::forwStride2Read_Word32 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 2, reading in 32-bit chunks.
- int32_t xmem::forwStride2Read_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 2, reading in 64-bit chunks.
- int32_t xmem::forwStride2Read_Word128 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 2, reading in 128-bit chunks.
- int32_t xmem::forwStride2Read_Word256 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 2, reading in 256-bit chunks.
- int32_t xmem::revStride2Read_Word32 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 2, reading in 32-bit chunks.
- int32_t xmem::revStride2Read_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 2, reading in 64-bit chunks.
- int32_t xmem::revStride2Read_Word128 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 2, reading in 128-bit chunks.
- int32_t xmem::revStride2Read_Word256 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 2, reading in 256-bit chunks.
- int32_t xmem::forwStride2Write_Word32 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 2, writing in 32-bit chunks.
- int32_t xmem::forwStride2Write_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 2, writing in 64-bit chunks.
- int32_t xmem::forwStride2Write_Word128 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 2, writing in 128-bit chunks.
- int32_t xmem::forwStride2Write_Word256 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 2. writing in 256-bit chunks.
- int32_t xmem::revStride2Write_Word32 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 2, writing in 32-bit chunks.
- int32_t xmem::revStride2Write_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 2, writing in 64-bit chunks.
- int32_t xmem::revStride2Write_Word128 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 2, writing in 128-bit chunks.
- int32_t xmem::revStride2Write_Word256 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 2, writing in 256-bit chunks.
- int32_t xmem::forwStride4Read_Word32 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 4, reading in 32-bit chunks.
- int32_t xmem::forwStride4Read_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 4, reading in 64-bit chunks.
- int32_t xmem::forwStride4Read_Word128 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 4, reading in 128-bit chunks.
- int32_t xmem::forwStride4Read_Word256 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 4, reading in 256-bit chunks.
- int32_t xmem::revStride4Read_Word32 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 4, reading in 32-bit chunks.
- int32_t xmem::revStride4Read_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 4, reading in 64-bit chunks.
- int32_t xmem::revStride4Read_Word128 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 4, reading in 128-bit chunks.
- int32_t xmem::revStride4Read_Word256 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 4, reading in 256-bit chunks.
- int32_t xmem::forwStride4Write_Word32 (void *start_address, void *end_address)

Walks over the allocated memory in forward strides of size 4, writing in 32-bit chunks.

- int32_t xmem::forwStride4Write_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 4, writing in 64-bit chunks.
- int32 t xmem::forwStride4Write Word128 (void *start address, void *end address)
 - Walks over the allocated memory in forward strides of size 4, writing in 128-bit chunks.
- int32_t xmem::forwStride4Write_Word256 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 4, writing in 256-bit chunks.
- int32_t xmem::revStride4Write_Word32 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 4, writing in 32-bit chunks.
- int32_t xmem::revStride4Write_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 4, writing in 64-bit chunks.
- int32_t xmem::revStride4Write_Word128 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 4, writing in 128-bit chunks.
- int32_t xmem::revStride4Write_Word256 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 4, writing in 256-bit chunks.
- int32_t xmem::forwStride8Read_Word32 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 8, reading in 32-bit chunks.
- int32_t xmem::forwStride8Read_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 8, reading in 64-bit chunks.
- int32_t xmem::forwStride8Read_Word128 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 8, reading in 128-bit chunks.
- int32_t xmem::forwStride8Read_Word256 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 8, reading in 256-bit chunks.
- int32_t xmem::revStride8Read_Word32 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 8, reading in 32-bit chunks.
- int32_t xmem::revStride8Read_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 8, reading in 64-bit chunks.
- int32_t xmem::revStride8Read_Word128 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 8, reading in 128-bit chunks.
- int32_t xmem::revStride8Read_Word256 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 8, reading in 256-bit chunks.
- int32_t xmem::forwStride8Write_Word32 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 8, writing in 32-bit chunks.
- int32_t xmem::forwStride8Write_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 8, writing in 64-bit chunks.
- int32_t xmem::forwStride8Write_Word128 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 8, writing in 128-bit chunks.
- int32_t xmem::forwStride8Write_Word256 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 8, writing in 256-bit chunks.
- int32_t xmem::revStride8Write_Word32 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 8, writing in 32-bit chunks.
- int32_t xmem::revStride8Write_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 8, writing in 64-bit chunks.
- int32_t xmem::revStride8Write_Word128 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 8, writing in 128-bit chunks.
- int32_t xmem::revStride8Write_Word256 (void *start_address, void *end_address)

 Walks over the allocated memory in reverse strides of size 8, writing in 256-bit chunks.
- int32_t xmem::forwStride16Read_Word32 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 16, reading in 32-bit chunks.
- int32_t xmem::forwStride16Read_Word64 (void *start_address, void *end_address)

 Walks over the allocated memory in forward strides of size 16, reading in 64-bit chunks.

• int32_t xmem::forwStride16Read_Word128 (void *start_address, void *end_address)

Walks over the allocated memory in forward strides of size 16, reading in 128-bit chunks.

• int32_t xmem::forwStride16Read_Word256 (void *start_address, void *end_address)

Walks over the allocated memory in forward strides of size 16, reading in 256-bit chunks.

int32_t xmem::revStride16Read_Word32 (void *start_address, void *end_address)

Walks over the allocated memory in reverse strides of size 16, reading in 32-bit chunks.

int32_t xmem::revStride16Read_Word64 (void *start_address, void *end_address)

Walks over the allocated memory in reverse strides of size 16, reading in 64-bit chunks.

• int32_t xmem::revStride16Read_Word128 (void *start_address, void *end_address)

Walks over the allocated memory in reverse strides of size 16, reading in 128-bit chunks.

• int32_t xmem::revStride16Read_Word256 (void *start_address, void *end_address)

Walks over the allocated memory in reverse strides of size 16, reading in 256-bit chunks.

• int32_t xmem::forwStride16Write_Word32 (void *start_address, void *end_address)

Walks over the allocated memory in forward strides of size 16, writing in 32-bit chunks.

int32_t xmem::forwStride16Write_Word64 (void *start_address, void *end_address)

Walks over the allocated memory in forward strides of size 16, writing in 64-bit chunks.

• int32 t xmem::forwStride16Write Word128 (void *start address, void *end address)

Walks over the allocated memory in forward strides of size 16, writing in 128-bit chunks.

int32_t xmem::forwStride16Write_Word256 (void *start_address, void *end_address)

Walks over the allocated memory in forward strides of size 16, writing in 256-bit chunks.

• int32_t xmem::revStride16Write_Word32 (void *start_address, void *end_address)

Walks over the allocated memory in reverse strides of size 16, writing in 32-bit chunks.

• int32 t xmem::revStride16Write Word64 (void *start address, void *end address)

Walks over the allocated memory in reverse strides of size 16, writing in 64-bit chunks.

• int32 t xmem::revStride16Write Word128 (void *start address, void *end address)

Walks over the allocated memory in reverse strides of size 16, writing in 128-bit chunks.

int32_t xmem::revStride16Write_Word256 (void *start_address, void *end_address)

Walks over the allocated memory in reverse strides of size 16, writing in 256-bit chunks.

int32_t xmem::randomRead_Word64 (uintptr_t *first_address, uintptr_t **last_touched_address, size_-t len)

Walks over the allocated memory in random order by chasing 64-bit pointers.

• int32_t xmem::randomRead_Word128 (uintptr_t *first_address, uintptr_t **last_touched_address, size_t len)

Walks over the allocated memory in random order by chasing 64-bit pointers embedded in 128-bit memory words.

• int32_t xmem::randomRead_Word256 (uintptr_t *first_address, uintptr_t **last_touched_address, size_t len)

Walks over the allocated memory in random order by chasing 64-bit pointers embedded in 256-bit memory words.

• int32_t xmem::randomWrite_Word64 (uintptr_t *first_address, uintptr_t **last_touched_address, size_t len)

Walks over the allocated memory in random order by chasing 64-bit pointers. A pointer is read and written back with the same value before chasing to the next pointer. Thus, each memory address is a read followed by immediate write operation.

int32_t xmem::randomWrite_Word128 (uintptr_t *first_address, uintptr_t **last_touched_address, size_t len)

Walks over the allocated memory in random order by chasing 64-bit pointers embedded within 128-bit words. A 128-bit word is read and written back with the same value before chasing to the next location extracted as a 64-bit address in the 128-bit word. Thus, each memory address is a read followed by immediate write operation as well as a vector word extraction.

int32_t xmem::randomWrite_Word256 (uintptr_t *first_address, uintptr_t **last_touched_address, size_t len)

Walks over the allocated memory in random order by chasing 64-bit pointers embedded within 256-bit words. A 256-bit word is read and written back with the same value before chasing to the next location extracted as a 64-bit address in the 256-bit word. Thus, each memory address is a read followed by immediate write operation as well as a vector word extraction.

6.9.1 Detailed Description

Header file for benchmark kernel functions for doing the actual work we care about. :)

6.10 src/include/BenchmarkManager.h File Reference

Header file for the BenchmarkManager class.

```
#include <common.h>
#include <Timer.h>
#include <PowerReader.h>
#include <Benchmark.h>
#include <ThroughputBenchmark.h>
#include <LatencyBenchmark.h>
#include <Configurator.h>
#include <cstdint>
#include <vector>
#include <fstream>
```

Classes

· class xmem::BenchmarkManager

Manages running all benchmarks at a high level.

6.10.1 Detailed Description

Header file for the BenchmarkManager class.

6.11 src/include/common.h File Reference

Header file for common preprocessor definitions, macros, functions, and global constants.

```
#include <cstdint>
#include <cstddef>
```

Macros

- #define **VERSION** "2.1.7"
- #define KB 1024
- #define MB 1048576
- #define MB_4 4194304
- #define MB_16 16777216
- #define MB 64 67108864
- #define MB_256 268435456
- #define **MB_512** 536870912
- #define GB 1073741824
- #define **GB_4** 4294967296
- #define DEFAULT PAGE SIZE 4*KB
- #define DEFAULT LARGE PAGE SIZE 2*MB
- #define DEFAULT_WORKING_SET_SIZE_PER_THREAD DEFAULT_PAGE_SIZE

- #define DEFAULT_NUM_WORKER_THREADS 1
- #define DEFAULT NUM NODES 0
- #define DEFAULT_NUM_PHYSICAL_PACKAGES 0
- #define DEFAULT_NUM_PHYSICAL_CPUS 0
- #define DEFAULT_NUM_LOGICAL_CPUS 0
- #define DEFAULT_NUM_L1_CACHES 0
- #define DEFAULT NUM L2 CACHES 0
- #define DEFAULT_NUM_L3_CACHES 0
- #define DEFAULT_NUM_L4_CACHES 0
- #define MIN ELAPSED TICKS 10000
- #define UNROLL2(x) x x
- #define **UNROLL4**(x) UNROLL2(x) UNROLL2(x)
- #define UNROLL8(x) UNROLL4(x) UNROLL4(x)
- #define UNROLL16(x) UNROLL8(x) UNROLL8(x)
- #define UNROLL32(x) UNROLL16(x) UNROLL16(x)
- #define UNROLL64(x) UNROLL32(x) UNROLL32(x)
- #define UNROLL128(x) UNROLL64(x) UNROLL64(x)
- #define UNROLL256(x) UNROLL128(x) UNROLL128(x)
- #define UNROLL512(x) UNROLL256(x) UNROLL256(x)
- #define UNROLL1024(x) UNROLL512(x) UNROLL512(x)
- #define UNROLL2048(x) UNROLL1024(x) UNROLL1024(x)
- #define UNROLL4096(x) UNROLL2048(x) UNROLL2048(x)
- #define UNROLL8192(x) UNROLL4096(x) UNROLL4096(x)
- #define UNROLL16384(x) UNROLL8192(x) UNROLL8192(x)
- #define UNROLL32768(x) UNROLL16384(x) UNROLL16384(x)
- #define UNROLL65536(x) UNROLL32768(x) UNROLL32768(x)
- #define LATENCY_BENCHMARK_UNROLL_LENGTH 512
- #define USE TSC TIMER
- #define USE_TIME_BASED_BENCHMARKS
- #define BENCHMARK DURATION SEC 4
- #define THROUGHPUT_BENCHMARK_BYTES_PER_PASS 4096
- #define POWER SAMPLING_PERIOD_MS 1000
- #define EXT_DELAY_INJECTED_LOADED_LATENCY_BENCHMARK

Typedefs

• typedef uint32 t xmem::Word32 t

Enumerations

• enum pattern mode t { SEQUENTIAL, RANDOM, NUM PATTERN MODES }

Memory access patterns are broadly categorized by sequential or random-access.

enum rw_mode_t { READ, WRITE, NUM_RW_MODES }

Memory access batterns are broadly categorized by reads and writes.

enum chunk_size_t {
 CHUNK_32b, CHUNK_64b, CHUNK_128b, CHUNK_256b,
 NUM_CHUNK_SIZES }

Legal memory read/write chunk sizes in bits.

enum ext_t { EXT_NUM_DELAY_INJECTED_LOADED_LATENCY_BENCHMARK, NUM_EXTENSIONS }

Functions

• void xmem::print_welcome_message ()

Prints a basic welcome message to the console with useful information.

void xmem::print_types_report ()

Prints the various C/C++ types to the console for this machine.

void xmem::print compile time options ()

Prints compile-time option information to the console.

void xmem::setup_timer ()

Initializes the timer and outputs results to the console for sanity checking.

void xmem::report_timer ()

Reports timer info to the console.

void xmem::test_thread_affinities ()

Checks to see if the calling thread can be locked to all logical CPUs in the system, and reports to the console the progress.

• bool xmem::lock thread to numa node (uint32 t numa node)

Sets the affinity of the calling thread to the lowest numbered logical CPU in the given NUMA node. TODO: Improve this functionality, it is quite limiting.

bool xmem::unlock_thread_to_numa_node ()

Clears the affinity of the calling thread to any given NUMA node.

bool xmem::lock_thread_to_cpu (uint32_t cpu_id)

Sets the affinity of the calling thread to a given logical CPU.

bool xmem::unlock thread to cpu ()

Clears the affinity of the calling thread to any given logical CPU.

• int32_t xmem::cpu_id_in_numa_node (uint32_t numa_node, uint32_t cpu_in_node)

Gets the CPU ID for a logical CPU of interest in a particular NUMA node. For example, if numa_node is 1 and cpu_-in_node is 2, and there are 4 logical CPUs per node, then this will give the answer 6 (6th CPU), assuming CPU IDs start at 0.

size_t xmem::compute_number_of_passes (size_t working_set_size_KB)

Computes the number of passes to use for a given working set size in KB, when size-based benchmarking mode is enabled at compile-time. You may want to change this implementation to suit your needs. See the compile-time options in common.h.

bool xmem::config_page_size ()

Queries the page sizes from the system and sets relevant global variables.

void xmem::init_globals ()

Initializes useful global variables.

• int32_t xmem::query_sys_info ()

Sets up global variables based on system information at runtime.

void xmem::report_sys_info ()

Reports the system configuration to the console as indicated by global variables.

uint64_t xmem::start_timer ()

Query the timer for the start of a timed section of code.

uint64_t xmem::stop_timer ()

Query the timer for the end of a timed section of code.

6.11.1 Detailed Description

Header file for common preprocessor definitions, macros, functions, and global constants.

6.11.2 Macro Definition Documentation

6.11.2.1 #define BENCHMARK_DURATION_SEC 4

RECOMMENDED VALUE: At least 2. Number of seconds to run in each benchmark.

6.11.2.2 #define DEFAULT_LARGE_PAGE_SIZE 2*MB

Default platform large page size in bytes. This generally should not be relied on, but is a failsafe.

6.11.2.3 #define DEFAULT_NUM_L1_CACHES 0

Default number of L1 caches.

6.11.2.4 #define DEFAULT_NUM_L2_CACHES 0

Default number of L2 caches.

6.11.2.5 #define DEFAULT_NUM_L3_CACHES 0

Default number of L3 caches.

6.11.2.6 #define DEFAULT_NUM_L4_CACHES 0

Default number of L4 caches.

6.11.2.7 #define DEFAULT_NUM_LOGICAL_CPUS 0

Default number of logical CPU cores.

6.11.2.8 #define DEFAULT_NUM_NODES 0

Default number of NUMA nodes.

6.11.2.9 #define DEFAULT_NUM_PHYSICAL_CPUS 0

Default number of physical CPU cores.

6.11.2.10 #define DEFAULT_NUM_PHYSICAL_PACKAGES 0

Default number of physical packages.

6.11.2.11 #define DEFAULT NUM WORKER THREADS 1

Default number of worker threads to use.

6.11.2.12 #define DEFAULT_PAGE_SIZE 4*KB

Default platform page size in bytes. This generally should not be relied on, but is a failsafe.

6.11.2.13 #define DEFAULT_WORKING_SET_SIZE_PER_THREAD DEFAULT_PAGE_SIZE

Default working set size in bytes.

6.11.2.14 #define EXT_DELAY_INJECTED_LOADED_LATENCY_BENCHMARK

RECOMMENDED ENABLED. This allows for a custom extension to X-Mem that performs latency benchmarking with forward sequential 64-bit and 256-bit read-based load threads with variable delays injected in between memory accesses.

6.11.2.15 #define LATENCY_BENCHMARK_UNROLL_LENGTH 512

Number of unrolls in the latency benchmark pointer chasing core function.

6.11.2.16 #define MIN_ELAPSED_TICKS 10000

If any routine measured fewer than this number of ticks its results should be viewed with suspicion. This is because the latency of the timer itself will matter.

6.11.2.17 #define POWER_SAMPLING_PERIOD_MS 1000

RECOMMENDED VALUE: 1000. Sampling period in milliseconds for all power measurement mechanisms.

6.11.2.18 #define THROUGHPUT_BENCHMARK_BYTES_PER_PASS 4096

RECOMMENDED VALUE: 4096. Number of bytes read or written per pass of any ThroughputBenchmark. This must be less than or equal to the minimum working set size, which is currently 4 KB.

6.11.2.19 #define USE_TIME_BASED_BENCHMARKS

RECOMMENDED ENABLED. All benchmarks run for an estimated amount of time, and the figures of merit are computed based on the amount of memory accesses completed in the time limit. This mode has more consistent runtime across different machines, memory performance, and working set sizes, but may have more conservative measurements for differing levels of cache hierarchy (overestimating latency and underestimating throughput).

6.11.2.20 #define USE_TSC_TIMER

RECOMMENDED ENABLED. Use the Intel Time Stamp Counter native hardware timer. Only use this if you know what you are doing.

6.12 src/include/Configurator.h File Reference

Header file for the Configurator class and some helper data structures.

```
#include <common.h>
#include <optionparser.h>
#include <MyArg.h>
#include <cstdint>
#include <string>
```

Classes

· class xmem::Configurator

Handles all user input interpretation and generates the necessary flags for running benchmarks.

Enumerations

enum optionIndex {
 UNKNOWN, ALL, CHUNK_SIZE, EXTENSION,
 OUTPUT_FILE, HELP, BASE_TEST_INDEX, NUM_WORKER_THREADS,
 MEAS_LATENCY, ITERATIONS, RANDOM_ACCESS_PATTERN, SEQUENTIAL_ACCESS_PATTERN,
 MEAS_THROUGHPUT, NUMA_DISABLE, VERBOSE, WORKING_SET_SIZE_PER_THREAD,
 USE_LARGE_PAGES, USE_READS, USE_WRITES, STRIDE_SIZE }

Enumerates all possible types of command-line options.

Variables

• const Descriptor xmem::usage []

Command-line option descriptors as needed by stuff in optionparser.h>. This is basically the help message content.

6.12.1 Detailed Description

Header file for the Configurator class and some helper data structures.

6.13 src/include/ExampleArg.h File Reference

Slightly-modified third-party code related to OptionParser.

```
#include <optionparser.h>
#include <cstdint>
#include <stdio.h>
```

Classes

· class xmem::ExampleArg

6.13.1 Detailed Description

Slightly-modified third-party code related to OptionParser.

6.14 src/include/ext/DelayInjectedLoadedLatencyBenchmark/delay_injected_benchmark_kernels.h File Reference

Header file for benchmark kernel functions with integrated delays for doing the actual work we care about. :)

```
#include <cstdint>
```

Macros

- #define my_nop2() my_nop(); my_nop()
- #define my_nop4() my_nop2(); my_nop2()
- #define **my_nop8**() my_nop4(); my_nop4()
- #define my_nop16() my_nop8(); my_nop8()
- #define my_nop32() my_nop16(); my_nop16()
- #define my_nop64() my_nop32(); my_nop32()
- #define my_nop128() my_nop64(); my_nop64()
- #define my_nop256() my_nop128(); my_nop128()
- #define my nop512() my nop256(); my nop256()
- #define my_nop1024() my_nop512(); my_nop512()

Functions

- int32_t xmem::dummy_forwSequentialLoop_Word64_Delay1 (void *start_address, void *end_address)

 Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.
- int32_t xmem::dummy_forwSequentialLoop_Word64_Delay2 (void *start_address, void *end_address)

 Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.
- int32_t xmem::dummy_forwSequentialLoop_Word64_Delay4 (void *start_address, void *end_address)

 Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.
- int32_t xmem::dummy_forwSequentialLoop_Word64_Delay8 (void *start_address, void *end_address)

 Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.
- int32_t xmem::dummy_forwSequentialLoop_Word64_Delay16 (void *start_address, void *end_address)

 Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.
- int32_t xmem::dummy_forwSequentialLoop_Word64_Delay32 (void *start_address, void *end_address)

 Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.
- int32_t xmem::dummy_forwSequentialLoop_Word64_Delay64 (void *start_address, void *end_address)
 Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.
- int32_t xmem::dummy_forwSequentialLoop_Word64_Delay128 (void *start_address, void *end_-address)

Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.

- int32_t xmem::dummy_forwSequentialLoop_Word64_Delay256plus (void *start_address, void *end_-address)
 - Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.
- int32_t xmem::dummy_forwSequentialLoop_Word256_Delay1 (void *start_address, void *end_address)

 Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.
- int32_t xmem::dummy_forwSequentialLoop_Word256_Delay2 (void *start_address, void *end_address)

 Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.
- int32_t xmem::dummy_forwSequentialLoop_Word256_Delay4 (void *start_address, void *end_address)

 Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.
- int32_t xmem::dummy_forwSequentialLoop_Word256_Delay8 (void *start_address, void *end_address)

Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.

int32_t xmem::dummy_forwSequentialLoop_Word256_Delay16 (void *start_address, void *end_-address)

Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.

int32_t xmem::dummy_forwSequentialLoop_Word256_Delay32 (void *start_address, void *end_-address)

Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.

int32_t xmem::dummy_forwSequentialLoop_Word256_Delay64plus (void *start_address, void *end_-address)

Used for measuring the time spent doing everything in delay-injected forward sequential Word 64 loops except for the memory access and delays themselves.

• int32_t xmem::forwSequentialRead_Word64_Delay1 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 1 delays (nops) are inserted between memory instructions.

• int32 t xmem::forwSequentialRead Word64 Delay2 (void *start address, void *end address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 2 delays (nops) are inserted between memory instructions.

• int32 t xmem::forwSequentialRead Word64 Delay4 (void *start address, void *end address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 4 delays (nops) are inserted between memory instructions.

• int32_t xmem::forwSequentialRead_Word64_Delay8 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 8 delays (nops) are inserted between memory instructions.

• int32_t xmem::forwSequentialRead_Word64_Delay16 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 16 delays (nops) are inserted between memory instructions.

• int32_t xmem::forwSequentialRead_Word64_Delay32 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 32 delays (nops) are inserted between memory instructions.

• int32_t xmem::forwSequentialRead_Word64_Delay64 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 64 delays (nops) are inserted between memory instructions.

• int32_t xmem::forwSequentialRead_Word64_Delay128 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 128 delays (nops) are inserted between memory instructions.

int32_t xmem::forwSequentialRead_Word64_Delay256 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 256 delays (nops) are inserted between memory instructions.

• int32_t xmem::forwSequentialRead_Word64_Delay512 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 512 delays (nops) are inserted between memory instructions.

• int32_t xmem::forwSequentialRead_Word64_Delay1024 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 1024 delays (nops) are inserted between memory instructions.

int32_t xmem::forwSequentialRead_Word256_Delay1 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 1 delays (nops) are inserted between memory instructions.

• int32 t xmem::forwSequentialRead Word256 Delay2 (void *start address, void *end address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 2 delays (nops) are inserted between memory instructions.

• int32 t xmem::forwSequentialRead Word256 Delay4 (void *start address, void *end address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 4 delays (nops) are inserted between memory instructions.

int32_t xmem::forwSequentialRead_Word256_Delay8 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 8 delays (nops) are inserted between memory instructions.

• int32_t xmem::forwSequentialRead_Word256_Delay16 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 16 delays (nops) are inserted between memory instructions.

• int32 t xmem::forwSequentialRead Word256 Delay32 (void *start address, void *end address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 32 delays (nops) are inserted between memory instructions.

• int32 t xmem::forwSequentialRead Word256 Delay64 (void *start address, void *end address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 64 delays (nops) are inserted between memory instructions.

• int32 t xmem::forwSequentialRead Word256 Delay128 (void *start address, void *end address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 128 delays (nops) are inserted between memory instructions.

• int32 t xmem::forwSequentialRead Word256 Delay256 (void *start address, void *end address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 256 delays (nops) are inserted between memory instructions.

• int32_t xmem::forwSequentialRead_Word256_Delay512 (void *start_address, void *end_address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 512 delays (nops) are inserted between memory instructions.

• int32 t xmem::forwSequentialRead Word256 Delay1024 (void *start address, void *end address)

Walks over the allocated memory forward sequentially, reading in 64-bit chunks. 1024 delays (nops) are inserted between memory instructions.

6.14.1 Detailed Description

Header file for benchmark kernel functions with integrated delays for doing the actual work we care about. :)

6.15 src/include/ext/DelayInjectedLoadedLatencyBenchmark/DelayInjectedLoaded-LatencyBenchmark.h File Reference

Header file for the DelayInjectedLoadedLatencyBenchmark class.

6.15.1 Detailed Description

Header file for the DelayInjectedLoadedLatencyBenchmark class.

6.16 src/include/LatencyBenchmark.h File Reference

Header file for the LatencyBenchmark class.

```
#include <Benchmark.h>
#include <common.h>
#include <cstdint>
#include <string>
```

Classes

· class xmem::LatencyBenchmark

A type of benchmark that measures memory latency via random pointer chasing. Loading may be provided with separate threads which access memory as quickly as possible using given access patterns.

6.16.1 Detailed Description

Header file for the LatencyBenchmark class.

6.17 src/include/LatencyWorker.h File Reference

Header file for the LatencyWorker class.

```
#include <MemoryWorker.h>
#include <benchmark_kernels.h>
#include <common.h>
```

Classes

· class xmem::LatencyWorker

Multithreading-friendly class to do memory loading.

6.17.1 Detailed Description

Header file for the LatencyWorker class.

6.18 src/include/LoadWorker.h File Reference

Header file for the LoadWorker class.

```
#include <MemoryWorker.h>
#include <benchmark_kernels.h>
```

Classes

• class xmem::LoadWorker

Multithreading-friendly class to do memory loading.

6.18.1 Detailed Description

Header file for the LoadWorker class.

6.19 src/include/MemoryWorker.h File Reference

Header file for the MemoryWorker class.

```
#include <Runnable.h>
#include <cstdint>
```

Classes

· class xmem::MemoryWorker

Multithreading-friendly class to run memory access kernels.

6.19.1 Detailed Description

Header file for the MemoryWorker class.

6.20 src/include/MyArg.h File Reference

Extensions to third-party optionparser-related code.

```
#include <ExampleArg.h>
#include <cstdint>
#include <stdio.h>
#include <cstdlib>
```

Classes

class xmem::MyArg

6.20.1 Detailed Description

Extensions to third-party optionparser-related code.

6.21 src/include/optionparser.h File Reference

This is the only file required to use The Lean Mean C++ Option Parser. Just #include it and you're set.

Classes

struct xmem::Descriptor

Describes an option, its help text (usage) and how it should be parsed.

· class xmem::Option

A parsed option from the command line together with its argument if it has one.

struct xmem::Arg

Functions for checking the validity of option arguments.

struct xmem::Stats

Determines the minimum lengths of the buffer and options arrays used for Parser.

· class xmem::Parser

Checks argument vectors for validity and parses them into data structures that are easier to work with.

- struct xmem::Parser::Action
- class xmem::Stats::CountOptionsAction

- · class xmem::Parser::StoreOptionAction
- struct xmem::PrintUsageImplementation
- struct xmem::PrintUsageImplementation::IStringWriter
- struct xmem::PrintUsageImplementation::FunctionWriter< Function >
- struct xmem::PrintUsageImplementation::OStreamWriter< OStream >
- struct xmem::PrintUsageImplementation::TemporaryWriter< Temporary >
- struct xmem::PrintUsageImplementation::SyscallWriter< Syscall >
- struct xmem::PrintUsageImplementation::StreamWriter< Function, Stream >
- class xmem::PrintUsageImplementation::LinePartIterator
- class xmem::PrintUsageImplementation::LineWrapper

Typedefs

typedef ArgStatus(* xmem::CheckArg)(const Option & option, bool msg)
 Signature of functions that check if an argument is valid for a certain type of option.

Enumerations

enum ArgStatus { xmem::ARG_NONE, xmem::ARG_OK, xmem::ARG_IGNORE, xmem::ARG_ILLEGAL }

Possible results when checking if an argument is valid for a certain option.

Functions

template<typename OStream >
 void xmem::printUsage (OStream &prn, const Descriptor usage[], int width=80, int last_column_min_ percent=50, int last_column_own_line_max_percent=75)

Outputs a nicely formatted usage string with support for multi-column formatting and line-wrapping.

- template<typename Function >
 void xmem::printUsage (Function *prn, const Descriptor usage[], int width=80, int last_column_min_ percent=50, int last_column_own_line_max_percent=75)
- template<typename Temporary >
 void xmem::printUsage (const Temporary &prn, const Descriptor usage[], int width=80, int last_column_ min_percent=50, int last_column_own_line_max_percent=75)
- template<typename Syscall >
 void xmem::printUsage (Syscall *prn, int fd, const Descriptor usage[], int width=80, int last_column_min_ percent=50, int last_column_own_line_max_percent=75)
- template<typename Function, typename Stream > void xmem::printUsage (Function *prn, Stream *stream, const Descriptor usage[], int width=80, int last_column_min_percent=50, int last_column_own_line_max_percent=75)

6.21.1 Detailed Description

This is the only file required to use The Lean Mean C++ Option Parser. Just #include it and you're set. The Lean Mean C++ Option Parser handles the program's command line arguments (argc, argv). It supports the short and long option formats of getopt(), getopt_long() and getopt_long_only() but has a more convenient interface. The following features set it apart from other option parsers:

Highlights:

- It is a header-only library. Just #include "optionparser.h" and you're set.
- It is freestanding. There are no dependencies whatsoever, not even the C or C++ standard library.

- It has a usage message formatter that supports column alignment and line wrapping. This aids localization because it adapts to translated strings that are shorter or longer (even if they contain Asian wide characters).
- Unlike getopt() and derivatives it doesn't force you to loop through options sequentially. Instead you can access options directly like this:
 - Test for presence of a switch in the argument vector:

```
if ( options[QUIET] ) ...
```

- Evaluate -enable-foo/-disable-foo pair where the last one used wins:

```
if ( options[FOO].last()->type() == DISABLE ) ...
```

- Cumulative option (-v verbose, -vv more verbose, -vvv even more verbose):

```
int verbosity = options[VERBOSE].count();
```

- Iterate over all –file=<fname> arguments:

```
for (Option* opt = options[FILE]; opt; opt = opt->next())
fname = opt->arg; ...
```

- If you really want to, you can still process all arguments in order:

```
for (int i = 0; i < p.optionsCount(); ++i) {
   Option& opt = buffer[i];
   switch(opt.index()) {
    case HELP:
        case VERBOSE: ...
    case FILE:        fname = opt.arg; ...
    case UNKNOWN: ...</pre>
```

Despite these features the code size remains tiny. It is smaller than uClibc's GNU getopt() and just a couple 100 bytes larger than uClibc's SUSv3 getopt().

(This does not include the usage formatter, of course. But you don't have to use that.)

Download:

```
Tarball with examples and test programs: optionparser-1.3.tar.gz Just the header (this is all you really need): optionparser.h
```

Changelog:

Version 1.3: Compatible with Microsoft Visual C++.

Version 1.2: Added Option::namelen and removed the extraction of short option characters into a special buffer.

Changed Arg::Optional to accept arguments if they are attached rather than separate. This is what GNU getopt() does and how POSIX recommends utilities should interpret their arguments.

Version 1.1: Optional mode with argument reordering as done by GNU getopt(), so that options and non-options can be mixed. See Parser::parse().

Feedback:

Send questions, bug reports, feature requests etc. to: optionparser-feedback (a) lists.-sourceforge.net

Example program:

(Note: option::* identifiers are links that take you to their documentation.)

```
argc==(argc>0); argv+=(argc>0); // skip program name argv[0] if present
option::Stats stats(usage, argc, argv);
option::Option options[stats.options_max], buffer[stats.buffer_max];
option::Parser parse(usage, argc, argv, options, buffer);

if (parse.error())
    return 1;

if (options[HELP] || argc == 0) {
    option::printUsage(std::cout, usage);
    return 0;
}

std::cout << "--plus count: " <<
        options[PLUS].count() << "\n";

for (option::Option* opt = options[UNKNOWN]; opt; opt = opt->next())
    std::cout << "Unknown option: " << opt->name << "\n";

for (int i = 0; i < parse.nonOptionsCount(); ++i)
    std::cout << "Non-option #" << i << ": " << parse.nonOption(i) << "\n";
}</pre>
```

Option syntax:

- The Lean Mean C++ Option Parser follows POSIX getopt() conventions and supports GNU-style getopt_long() long options as well as Perl-style single-minus long options (getopt_long_-only()).
- short options have the format -X where X is any character that fits in a char.
- short options can be grouped, i.e. -X -Y is equivalent to -XY.
- a short option may take an argument either separate (-X foo) or attached (-Xfoo). You can make the parser accept the additional format -X=foo by registering X as a long option (in addition to being a short option) and enabling single-minus long options.
- an argument-taking short option may be grouped if it is the last in the group, e.g. -ABCXfoo or -ABCX foo (foo is the argument to the -X option).
- a lone minus character '-' is not treated as an option. It is customarily used where a file name is expected to refer to stdin or stdout.
- long options have the format -option-name.
- the option-name of a long option can be anything and include any characters. Even = characters will work, but don't do that.
- [optional] long options may be abbreviated as long as the abbreviation is unambiguous. You can set a minimum length for abbreviations.
- [optional] long options may begin with a single minus. The double minus form is always accepted, too.
- a long option may take an argument either separate (-option arg) or attached (-option=arg). In the attached form the equals sign is mandatory.
- an empty string can be passed as an attached long option argument: -option-name= . Note the distinction between an empty string as argument and no argument at all.
- an empty string is permitted as separate argument to both long and short options.
- Arguments to both short and long options may start with a '-' character. E.g. -X-X, -X or -long-X=-X. If -X and -long-X take an argument, that argument will be "-X" in all 3 cases.
- If using the built-in Arg::Optional, optional arguments must be attached.
- the special option (i.e. without a name) terminates the list of options. Everything that follows is a non-option argument, even if it starts with a '-' character. The itself will not appear in the parse results.
- the first argument that doesn't start with '-' or '-' and does not belong to a preceding argument-taking option, will terminate the option list and is the first non-option argument. All following command line arguments are treated as non-option arguments, even if they start with '-'.

NOTE: This behaviour is mandated by POSIX, but GNU getopt() only honours this if it is explicitly requested (e.g. by setting POSIXLY_CORRECT).

You can enable the GNU behaviour by passing true as first argument to e.g. Parser::parse().

Arguments that look like options (i.e. '-' followed by at least 1 character) but aren't, are NOT treated
as non-option arguments. They are treated as unknown options and are collected into a list of unknown
options for error reporting.

This means that in order to pass a first non-option argument beginning with the minus character it is required to use the – special option, e.g.

```
program -x -- --strange-filename
```

In this example, <code>-strange-filename</code> is a non-option argument. If the <code>-</code> were omitted, it would be treated as an unknown option.

See option::Descriptor::longopt for information on how to collect unknown options.

6.22 src/include/PowerReader.h File Reference

Header file for the PowerReader class.

```
#include <common.h>
#include <Runnable.h>
#include <cstdint>
#include <vector>
#include <string>
```

Classes

· class xmem::PowerReader

An abstract base class for measuring power from an arbitrary source. This class is runnable using a worker thread.

6.22.1 Detailed Description

Header file for the PowerReader class.

6.23 src/include/Runnable.h File Reference

Header file for the Runnable class.

```
#include <cstdint>
```

Classes

• class xmem::Runnable

A base class for any object that implements a thread-safe run() function for use by Thread objects.

6.23.1 Detailed Description

Header file for the Runnable class.

6.24 src/include/Thread.h File Reference

Header file for the Thread class.

```
#include <Runnable.h>
#include <cstdint>
```

Classes

· class xmem::Thread

a nice wrapped thread interface independent of particular OS API

6.24.1 Detailed Description

Header file for the Thread class.

6.25 src/include/ThroughputBenchmark.h File Reference

Header file for the ThroughputBenchmark class.

```
#include <Benchmark.h>
#include <common.h>
#include <cstdint>
#include <string>
```

Classes

· class xmem::ThroughputBenchmark

A type of benchmark that measures memory throughput.

6.25.1 Detailed Description

Header file for the ThroughputBenchmark class.

6.26 src/include/Timer.h File Reference

Header file for the Timer class.

```
#include <cstdint>
```

Classes

class xmem::Timer

This class abstracts some characteristics of simple high resolution stopwatch timer. However, due to the inability or complexity of abstracting shared hardware timers, this class does not actually provide start and stop functions.

6.26.1 Detailed Description

Header file for the Timer class.

6.27 src/include/win/win_common_third_party.h File Reference

Header file for some third-party helper code for working with Windows APIs.

6.27.1 Detailed Description

Header file for some third-party helper code for working with Windows APIs.

6.28 src/include/win/win_CPdhQuery.h File Reference

Header and implementation file for some third-party code for measuring Windows OS-exposed performance counters.

6.28.1 Detailed Description

Header and implementation file for some third-party code for measuring Windows OS-exposed performance counters.

6.29 src/include/win/WindowsDRAMPowerReader.h File Reference

Header file for the WindowsDRAMPowerReader class.

6.29.1 Detailed Description

Header file for the WindowsDRAMPowerReader class.

6.30 src/LatencyBenchmark.cpp File Reference

Implementation file for the LatencyBenchmark class.

```
#include <LatencyBenchmark.h>
#include <common.h>
#include <benchmark_kernels.h>
#include <MemoryWorker.h>
#include <LatencyWorker.h>
#include <LoadWorker.h>
#include <iostream>
#include <random>
#include <assert.h>
#include <time.h>
```

6.30.1 Detailed Description

Implementation file for the LatencyBenchmark class.

6.31 src/LatencyWorker.cpp File Reference

Implementation file for the LatencyWorker class.

```
#include <LatencyWorker.h>
#include <benchmark_kernels.h>
#include <common.h>
#include <iostream>
```

6.31.1 Detailed Description

Implementation file for the LatencyWorker class.

6.32 src/LoadWorker.cpp File Reference

Implementation file for the LoadWorker class.

```
#include <LoadWorker.h>
#include <benchmark_kernels.h>
#include <common.h>
#include <iostream>
```

6.32.1 Detailed Description

Implementation file for the LoadWorker class.

6.33 src/main.cpp File Reference

main entry point to the tool

```
#include <common.h>
#include <build_datetime.h>
#include <Configurator.h>
#include <BenchmarkManager.h>
#include <iostream>
#include <string>
```

Functions

6.33.1

int main (int argc, char *argv[])
 The main entry point to the program.

Detailed Description

main entry point to the tool This tool is designed to measure bandwidth and latency of the memory system using several access patterns, strides, and working set sizes. The primary goal is to measure DRAM performance, although it can also measure cache performance depending on the configuration.

6.34 src/MemoryWorker.cpp File Reference

Implementation file for the MemoryWorker class.

```
#include <MemoryWorker.h>
```

6.34.1 Detailed Description

Implementation file for the MemoryWorker class.

6.35 src/PowerReader.cpp File Reference

Implementation file for the PowerReader class.

```
#include <PowerReader.h>
#include <common.h>
#include <cstdint>
#include <vector>
#include <iostream>
```

6.35.1 Detailed Description

Implementation file for the PowerReader class.

6.36 src/Runnable.cpp File Reference

Implementation file for the Runnable class.

```
#include <Runnable.h>
#include <iostream>
```

Variables

· return false

6.36.1 Detailed Description

Implementation file for the Runnable class.

6.37 src/Thread.cpp File Reference

Implementation file for the Thread class.

```
#include <Thread.h>
#include <stdlib.h>
#include <iostream>
```

Variables

- · return false
- · return true

6.37.1 Detailed Description

Implementation file for the Thread class.

6.38 src/ThroughputBenchmark.cpp File Reference

Implementation file for the ThroughputBenchmark class.

```
#include <ThroughputBenchmark.h>
#include <common.h>
#include <LoadWorker.h>
#include <Thread.h>
#include <iostream>
#include <assert.h>
#include <time.h>
```

6.38.1 Detailed Description

Implementation file for the ThroughputBenchmark class.

6.39 src/Timer.cpp File Reference

Implementation file for the Timer class.

```
#include <Timer.h>
#include <common.h>
```

6.39.1 Detailed Description

Implementation file for the Timer class.

6.40 src/win/win_common_third_party.cpp File Reference

Implementation file for some third-party helper code for working with Windows APIs.

6.40.1 Detailed Description

Implementation file for some third-party helper code for working with Windows APIs.

6.41 src/win/WindowsDRAMPowerReader.cpp File Reference

Implementation file for the WindowsDRAMPowerReader class.

6	41.	1	Deta	iled	Desc	ription	1

 $Implementation\ file\ for\ the\ Windows DRAMPower Reader\ class.$

Index

\sim Thread	metricUnits
xmem::Thread, 69	xmem::Benchmark, 22
_acquireLock	name
xmem::Runnable, 63	xmem::Benchmark, 22
_adjusted_ticks	xmem::PowerReader, 61
xmem::MemoryWorker, 45	_ns_per_tick
_averageLoadMetric	xmem::Timer, 73
xmem::LatencyBenchmark, 38	_num_samples
_averageMetric	xmem::PowerReader, 61
xmem::Benchmark, 21	_num_worker_threads
_average_dram_power_socket	xmem::Benchmark, 22
xmem::Benchmark, 21	_obj_valid
_average_power	xmem::Benchmark, 22
xmem::PowerReader, 61	_passes
_bytes_per_pass	xmem::MemoryWorker, 46
xmem::MemoryWorker, 45	_pattern_mode
_chunk_size	xmem::Benchmark, 22
xmem::Benchmark, 21	_peak_dram_power_socket
_completed	xmem::Benchmark, 22
xmem::MemoryWorker, 45	_peak_power
_cpu_affinity	xmem::PowerReader, 61
xmem::MemoryWorker, 45	_power_trace
xmem::PowerReader, 61	xmem::PowerReader, 61
cpu node	_power_units
xmem::Benchmark, 21	xmem::PowerReader, 61
_dram_power_readers	_releaseLock
xmem::Benchmark, 21	xmem::Runnable, 63
_dram_power_threads	_run_core
xmem::Benchmark, 21	xmem::Benchmark, 17
_elapsed_dummy_ticks	xmem::LatencyBenchmark, 38
xmem::MemoryWorker, 46	xmem::ThroughputBenchmark, 72
_elapsed_ticks	_rw_mode
xmem::MemoryWorker, 46	xmem::Benchmark, 22
hasRun	_sampling_period
xmem::Benchmark, 21	xmem::PowerReader, 61
iterations	_start_power_threads
xmem::Benchmark, 21	xmem::Benchmark, 18
len	_stop_power_threads
xmem::Benchmark, 21	xmem::Benchmark, 18 stop signal
xmem::MemoryWorker, 46	_stop_signal xmem::PowerReader, 61
loadMetricOnIter	_stride_size
xmem::LatencyBenchmark, 38	xmem::Benchmark, 22
_mem_array	ticks_per_sec
xmem::Benchmark, 21	xmem::Timer, 73
xmem::MemoryWorker, 46	_warning
_mem_node	xmem::Benchmark, 22
xmem::Benchmark, 22	xmem::MemoryWorker, 46
_metricOnIter	and the state of t
xmem::Benchmark, 22	add

verse and Chate CF	
xmem::Stats, 65	xmem::Timer, 73
append	get_ticks_per_sec
xmem::Option, 49	xmem::Timer, 73
arg	getAdjustedTicks
xmem::Option, 51	xmem::MemoryWorker, 44
D 1	getAverageDRAMPower
Benchmark	xmem::Benchmark, 18
xmem::Benchmark, 17	getAverageMetric
BenchmarkManager	xmem::Benchmark, 18
xmem::BenchmarkManager, 23	getAveragePower
buffer_max	xmem::PowerReader, 59
xmem::Stats, 65	getAvgLoadMetric
	xmem::LatencyBenchmark, 38
calculateMetrics	
xmem::PowerReader, 59	getBytesPerPass
cancel	xmem::MemoryWorker, 44
xmem::Thread, 70	getCPUNode
check_arg	xmem::Benchmark, 18
xmem::Descriptor, 34	getChunkSize
clear	xmem::Benchmark, 18
xmem::PowerReader, 59	getElapsedDummyTicks
clear_and_reset	xmem::MemoryWorker, 44
xmem::PowerReader, 59	getElapsedTicks
	xmem::MemoryWorker, 45
common.h	getExitCode
DEFAULT_NUM_NODES, 88	xmem::Thread, 70
DEFAULT_PAGE_SIZE, 88	getIterations
MIN_ELAPSED_TICKS, 89	
USE_TSC_TIMER, 89	xmem::Benchmark, 18
completed	getIterationsPerTest
xmem::Thread, 70	xmem::Configurator, 28
configureFromInput	getLastSample
xmem::Configurator, 26	xmem::PowerReader, 59
count	getLen
xmem::Option, 49	xmem::Benchmark, 19
CountOptionsAction	xmem::MemoryWorker, 45
xmem::Stats::CountOptionsAction, 33	getLoadMetricOnIter
create_and_start	xmem::LatencyBenchmark, 38
xmem::Thread, 70	getMemNode
	xmem::Benchmark, 19
created	getMetricOnIter
xmem::Thread, 70	_
DEFAULT NUM NODES	xmem::Benchmark, 19
common.h, 88	getMetricUnits
	xmem::Benchmark, 19
DEFAULT_PAGE_SIZE	getName
common.h, 88	xmem::Benchmark, 19
desc	getNumSamples
xmem::Option, 51	xmem::PowerReader, 59
	getNumThreads
error	xmem::Benchmark, 19
xmem::Parser, 55	getNumWorkerThreads
extensionsEnabled	xmem::Configurator, 28
xmem::Configurator, 28	getOutputFilename
	xmem::Configurator, 28
finished	_
xmem::Parser::Action, 13	getPasses
xmem::Parser::StoreOptionAction, 67	xmem::MemoryWorker, 45
first	getPatternMode
xmem::Option, 49	xmem::Benchmark, 20
	are ADe als DD AMDerrors
	getPeakDRAMPower xmem::Benchmark, 20

getPeakPower	MIN_ELAPSED_TICKS
xmem::PowerReader, 60	common.h, 89
getPowerTrace	MemoryWorker
xmem::PowerReader, 60	xmem::MemoryWorker, 44
getPowerUnits	
xmem::PowerReader, 60	name
getRWMode	xmem::Option, 52
xmem::Benchmark, 20	xmem::PowerReader, 60
getSamplingPeriod	namelen
xmem::PowerReader, 60	xmem::Option, 52
getStartingTestIndex	next
xmem::Configurator, 28	xmem::Option, 50
getStrideSize	xmem::PrintUsageImplementation::LinePart-
xmem::Benchmark, 20	Iterator, 40
getTarget	nextRow
xmem::Thread, 70	xmem::PrintUsageImplementation::LinePart-
getWorkingSetSizePerThread	Iterator, 40
xmem::Configurator, 28	nextTable
Amemoomigurator, 20	xmem::PrintUsageImplementation::LinePart-
hadWarning	Iterator, 40
xmem::MemoryWorker, 45	nextwrap
hasRun	xmem::Option, 50
xmem::Benchmark, 20	nonOptions
help	xmem::Parser, 55
xmem::Descriptor, 34	nonOptionsCount
index.	xmem::Parser, 55
index	and the second Continue
xmem::Descriptor, 34	operator const Option *
isFirst	xmem::Option, 50
xmem::Option, 49	operator Option *
isLast	xmem::Option, 50
xmem::Option, 49	operator=
isNUMAEnabled	xmem::Option, 50
xmem::Configurator, 28	Option
isThreadRunning	xmem::Option, 48
xmem::Thread, 70	options_max
isThreadSuspended	xmem::Stats, 65
xmem::Thread, 70	optionsCount
isValid	xmem::Parser, 56
xmem::Benchmark, 20	
isWideChar	parse
xmem::PrintUsageImplementation, 62	xmem::Parser, 56
3 1 ,	Parser
join	xmem::Parser, 54
xmem::Thread, 71	perform
,	xmem::Parser::Action, 13
last	xmem::Parser::StoreOptionAction, 67
xmem::Option, 49	xmem::Stats::CountOptionsAction, 33
latencyTestSelected	PowerReader
xmem::Configurator, 29	xmem::PowerReader, 58
LatencyWorker	
xmem::LatencyWorker, 39	prev
	xmem::Option, 51
LineWrapper	prevwrap
xmem::PrintUsageImplementation::LineWrapper,	xmem::Option, 51
41	process
LoadWorker	xmem::PrintUsageImplementation::LineWrapper,
xmem::LoadWorker, 42	41
longopt	
xmem::Descriptor, 34	run

xmem::Benchmark, 20	src/win/win_common_third_party.cpp, 104
runAll	started
xmem::BenchmarkManager, 23	xmem::Thread, 71
runExtDelayInjectedLoadedLatencyBenchmark	Stats
xmem::Configurator, 29	xmem::Stats, 65
runLatencyBenchmarks	stop
xmem::BenchmarkManager, 23	xmem::PowerReader, 60
runThroughputBenchmarks	StoreOptionAction
xmem::BenchmarkManager, 24	xmem::Parser::StoreOptionAction, 66
setUseOutputFile	Thread
xmem::Configurator, 29	xmem::Thread, 69
shortopt	throughputTestSelected
xmem::Descriptor, 35	xmem::Configurator, 29
src/Benchmark.cpp, 75	type
src/BenchmarkManager.cpp, 76	xmem::Descriptor, 35
src/Configurator.cpp, 77	xmem::Option, 51
src/LatencyBenchmark.cpp, 101	America Option, or
src/LatencyWorker.cpp, 102	USE TSC TIMER
src/LoadWorker.cpp, 102	common.h, 89
src/MemoryWorker.cpp, 103	useChunk128b
src/PowerReader.cpp, 103	xmem::Configurator, 29
src/Runnable.cpp, 103	useChunk256b
src/Thread.cpp, 103	xmem::Configurator, 29
src/ThroughputBenchmark.cpp, 104	useChunk32b
src/Timer.cpp, 104	xmem::Configurator, 29
src/benchmark_kernels.cpp, 75	useChunk64b
src/common.cpp, 76	xmem::Configurator, 30
• •	useLargePages
src/ext/DelayInjectedLoadedLatencyBenchmark/Delay-	xmem::Configurator, 30
InjectedLoadedLatencyBenchmark.cpp, 77	useOutputFile
src/ext/DelayInjectedLoadedLatencyBenchmark/delay	•
injected_benchmark_kernels.cpp, 77	xmem::Configurator, 30 useRandomAccessPattern
src/include/Benchmark.h, 78	xmem::Configurator, 30
src/include/BenchmarkManager.h, 85	•
src/include/Configurator.h, 89	useReads
src/include/ExampleArg.h, 90	xmem::Configurator, 30
src/include/LatencyBenchmark.h, 93	useSequentialAccessPattern
src/include/LatencyWorker.h, 94	xmem::Configurator, 30
src/include/LoadWorker.h, 94	useStrideN1
src/include/MemoryWorker.h, 94	xmem::Configurator, 30
src/include/MyArg.h, 95	useStrideN16
src/include/PowerReader.h, 99	xmem::Configurator, 31
src/include/Runnable.h, 99	useStrideN2
src/include/Thread.h, 100	xmem::Configurator, 31
src/include/ThroughputBenchmark.h, 100	useStrideN4
src/include/Timer.h, 100	xmem::Configurator, 31
src/include/benchmark_kernels.h, 78	useStrideN8
src/include/common.h, 85	xmem::Configurator, 31
src/include/ext/DelayInjectedLoadedLatencyBenchmark/-	
DelayInjectedLoadedLatencyBenchmark.h,	xmem::Configurator, 31
93	useStrideP16
src/include/ext/DelayInjectedLoadedLatencyBenchmark/d	elay- xmem::Configurator, 31
_injected_benchmark_kernels.h, 90	useStrideP2
src/include/optionparser.h, 95	xmem::Configurator, 31
src/include/win/WindowsDRAMPowerReader.h, 101	useStrideP4
src/include/win/win_CPdhQuery.h, 101	xmem::Configurator, 32
src/include/win/win_common_third_party.h, 101	useStrideP8
src/main.cpp, 102	xmem::Configurator, 32
src/win/WindowsDRAMPowerReader.cpp, 104	useWrites

xmem::Configurator, 32	extensionsEnabled, 28
validTava et	getIterationsPerTest, 28
validTarget	getNumWorkerThreads, 28
xmem::Thread, 71	getOutputFilename, 28
verboseMode	getStartingTestIndex, 28
xmem::Configurator, 32	getWorkingSetSizePerThread, 28
xmem::Arg, 14	isNUMAEnabled, 28
xmem::Benchmark, 15	latencyTestSelected, 29
_averageMetric, 21	runExtDelayInjectedLoadedLatencyBenchmark, 29
_average_dram_power_socket, 21	setUseOutputFile, 29
_chunk_size, 21	throughputTestSelected, 29
_cpu_node, 21	useChunk128b, 29
_dram_power_readers, 21	useChunk256b, 29
_dram_power_threads, 21	useChunk32b, 29
_hasRun, 21	useChunk64b, 30
_iterations, 21	useLargePages, 30
_len, 21	useOutputFile, 30
_mem_array, 21	useRandomAccessPattern, 30
_mem_node, 22	useReads, 30
_metricOnIter, 22	useSequentialAccessPattern, 30
_metricUnits, 22	useStrideN1, 30
_name, 22	useStrideN16, 31
num worker threads, 22	useStrideN2, 31
_ham_worker_threads, 22 _obj_valid, 22	useStrideN4, 31
_obj_valid, 22 _pattern_mode, 22	useStrideN8, 31
_peak_dram_power_socket, 22	useStrideP1, 31
_run_core, 17	useStrideP16, 31
_run_core, 17 _rw_mode, 22	useStrideP2, 31
_start_power_threads, 18	useStrideP4, 32
_stop_power_threads, 18	useStrideP8, 32
_stride_size, 22	useWrites, 32
stridesize, 22 _warning, 22	verboseMode, 32
Benchmark, 17	xmem::Descriptor, 33
getAverageDRAMPower, 18	check_arg, 34
getAverageMetric, 18	help, 34
getCPUNode, 18	index, 34
getChunkSize, 18	longopt, 34
getIterations, 18	shortopt, 35
getLen, 19	type, 35
getMemNode, 19	xmem::ExampleArg, 35
getMetricOnIter, 19	xmem::LatencyBenchmark, 37
getMetricUnits, 19	_averageLoadMetric, 38
getName, 19	_loadMetricOnIter, 38
getNumThreads, 19	_run_core, 38
getPatternMode, 20	getAvgLoadMetric, 38
getPeakDRAMPower, 20	getLoadMetricOnIter, 38
getRWMode, 20	xmem::LatencyWorker, 38
getStrideSize, 20	LatencyWorker, 39
hasRun, 20	xmem::LoadWorker, 41
isValid, 20	LoadWorker, 42
run, 20	xmem::MemoryWorker, 43
xmem::BenchmarkManager, 23	_adjusted_ticks, 45
BenchmarkManager, 23	_bytes_per_pass, 45
runAll, 23	_completed, 45
runLatencyBenchmarks, 23	_cpu_affinity, 45
runThroughputBenchmarks, 24	_elapsed_dummy_ticks, 46
xmem::Configurator, 24	_elapsed_ticks, 46
configureFromInput, 26	_erapsed_iteris, 40 _len, 46
Johngaror Tommpat, 20	_1011, 70

_mem_array, 46	clear_and_reset, 59
_passes, 46	getAveragePower, 59
_warning, 46	getLastSample, 59
getAdjustedTicks, 44	getNumSamples, 59
getBytesPerPass, 44	getPeakPower, 60
getElapsedDummyTicks, 44	getPowerTrace, 60
getElapsedTicks, 45	getPowerUnits, 60
getLen, 45	getSamplingPeriod, 60
getPasses, 45	name, 60
hadWarning, 45	PowerReader, 58
MemoryWorker, 44	stop, 60
xmem::MyArg, 46	xmem::PrintUsageImplementation, 62
xmem::Option, 47	isWideChar, 62
append, 49	xmem:: Print Usage Implementation:: Function Writer <
arg, 51	Function $>$, 36
count, 49	xmem::PrintUsageImplementation::IStringWriter, 36
desc, 51	xmem::PrintUsageImplementation::LinePartIterator, 39
first, 49	next, 40
isFirst, 49	nextRow, 40
isLast, 49	nextTable, 40
last, 49	xmem::PrintUsageImplementation::LineWrapper, 41
name, 52	LineWrapper, 41
namelen, 52	process, 41
next, 50	xmem::PrintUsageImplementation::OStreamWriter< O-
nextwrap, 50	Stream >, 52
operator const Option $*, 50$	xmem:: Print Usage Implementation:: Stream Writer <
operator Option $*, 50$	Function, Stream >, 67
operator=, 50	xmem::PrintUsageImplementation::SyscallWriter<
Option, 48	Syscall >, 68
prev, 51	xmem:: Print Usage Implementation:: Temporary Writer <
prevwrap, 51	Temporary >, 68
type, 51	xmem::Runnable, 62
xmem::Parser, 53	_acquireLock, 63
error, 55	_releaseLock, 63
nonOptions, 55	xmem::Stats, 64
nonOptionsCount, 55	add, 65
optionsCount, 56	buffer_max, 65
parse, 56	options_max, 65
Parser, 54	Stats, 65
xmem::Parser::Action, 13	xmem::Stats::CountOptionsAction, 32
finished, 13	CountOptionsAction, 33
perform, 13	perform, 33
xmem::Parser::StoreOptionAction, 66	xmem::Thread, 69
finished, 67	\sim Thread, 69
perform, 67	cancel, 70
StoreOptionAction, 66	completed, 70
xmem::PowerReader, 57	create_and_start, 70
_average_power, 61	created, 70
_cpu_affinity, 61	getExitCode, 70
_name, 61	getTarget, 70
_num_samples, 61	isThreadRunning, 70
_peak_power, 61	isThreadSuspended, 70
_power_trace, 61	join, 71
_power_units, 61	started, 71
_sampling_period, 61	Thread, 69
_stop_signal, 61	validTarget, 71
calculateMetrics, 59	xmem::ThroughputBenchmark, 71
clear, 59	_run_core, 72

```
xmem::Timer, 72
__ns_per_tick, 73
__ticks_per_sec, 73
get_ns_per_tick, 73
get_ticks_per_sec, 73
```