

# Pulse Secure Virtual Traffic Manager: Terraform Provider Reference Guide

Supporting Pulse Secure Virtual Traffic Manager 17.2r2

Product Release 17.2r2

Published 15 May, 2018

Document Version 1.0

Pulse Secure, LLC 2700 Zanker Road, Suite 200 San Jose CA 95134

www.pulsesecure.net

© 2018 by Pulse Secure, LLC. All rights reserved.

Pulse Secure and the Pulse Secure logo are trademarks of Pulse Secure, LLC in the United States. All other trademarks, service marks, registered trademarks, or registered service marks are the property of their respective owners.

Pulse Secure, LLC assumes no responsibility for any inaccuracies in this document. Pulse Secure, LLC reserves the right to change, modify, transfer, or otherwise revise this publication without notice.

Pulse Secure Virtual Traffic Manager: Terraform Provider Reference Guide

The information in this document is current as of the date on the title page.

#### **END USER LICENSE AGREEMENT**

The Pulse Secure product that is the subject of this technical documentation consists of (or is intended for use with) Pulse Secure software. Use of such software is subject to the terms and conditions of the End User License Agreement ("EULA") posted at <a href="http://www.pulsesecure.net/support/eula/">http://www.pulsesecure.net/support/eula/</a>. By downloading, installing or using such software, you agree to the terms and conditions of that EULA.

# Contents

PREFACE	1
DOCUMENT CONVENTIONS	1
Text formatting conventions	1
Command syntax conventions	1
Notes and Warnings	2
Requesting Technical Support	
Self-Help Online Tools and Resources	2
OPENING A CASE WITH PSGSC	
OVERVIEW	5
ABOUT THIS GUIDE	
Introducing the Traffic Manager	
Introducing the Terraform Provider	
GETTING STARTED	7
Installing the Traffic Manager Terraform Provider	7
Initializing the Terraform Provider	7
RESOURCE AND DATA SOURCE REFERENCE	9
ABOUT THE RESOURCE MODEL	9
Using the Resource Model	9
Configuration Resources	10
SETTING CONFIGURATION VALUES USING THE RESOURCE MODEL	10
Dependancy Tree	11
RESOURCE REFERENCE	11
VTM_ACTION_PROGRAM	11
VTM_ACTION	12
VTM_APTIMIZER_SCOPE	15
VTM_BGPNEIGHBOR	
VTM BANDWIDTH	17
VTM_APPLICATION_FIREWALL	18
VTM_CLOUD_API_CREDENTIAL	
VTM_CUSTOM	
VTM DNS SERVER ZONE	
VTM_DNS_SERVER_ZONE_FILE	
VTM_EVENT_TYPE	
VTM_EXTRA_FILE	

VTM_GLB_SERVICE	25
VTM_GLOBAL_SETTINGS	29
VTM_KERBEROS_KRB5CONF	60
VTM_KERBEROS_KEYTAB	60
VTM_KERBEROS_PRINCIPAL	61
VTM_LICENSE_KEY	62
VTM_LOCATION	62
VTM_LOG_EXPORT	63
VTM_MONITOR	65
VTM_MONITOR_SCRIPT	69
VTM_APPLIANCE_NAT	70
VTM_POOL	72
VTM_PROTECTION	84
VTM_RATE	88
VTM_RULE	89
VTM_SERVICE_LEVEL_MONITOR	89
VTM_SSL_CLIENT_KEY	90
VTM_SSL_SERVER_KEY	91
VTM_SSL_CA	92
VTM_SECURITY	92
VTM_PERSISTENCE	
VTM_TRAFFIC_IP_GROUP	95
VTM_TRAFFIC_MANAGER	98
VTM_RULE_AUTHENTICATOR	112
VTM_USER_AUTHENTICATOR	114
VTM_USER_GROUP	118
VTM_VIRTUAL_SERVER	120
VTM_APTIMIZER_PROFILE	147
Data Sources	148
Resources	148
Resource Lists	149
Statistics	150
VTM_ACTION_STATS	150
VTM_CACHE_ASP_SESSION_CACHE_STATS	
VTM_BANDWIDTH_STATS	152
VTM_CLOUD_API_CREDENTIAL_STATS	
VTM_CONNECTION_RATE_LIMIT_STATS	154
VTM_EVENT_STATS	
VTM_GLB_SERVICE_STATS	
VTM_GLOBALS_STATS	
VTM_TRAFFIC_IPS_IP_GATEWAY_STATS	
<del>_</del>	

VTM_CACHE_IP_SESSION_CACHE_STATS	164
VTM_CACHE_J2EE_SESSION_CACHE_STATS	165
VTM_LISTEN_IP_STATS	166
VTM_LOCATION_STATS	167
VTM_NETWORK_INTERFACE_STATS	168
VTM_NODES_NODE_STATS	169
VTM_NODES_NODE_INET46_STATS	170
VTM_PER_LOCATION_SERVICE_STATS	172
VTM_PER_NODE_SLM_PER_NODE_SERVICE_LEVEL_STATS	173
vtm_per_node_slm_per_node_service_level_inet46_stats	174
VTM_NODES_PER_POOL_NODE_STATS	175
VTM_POOL_STATS	178
VTM_RULE_AUTHENTICATOR_STATS	181
VTM_RULE_STATS	182
VTM_SERVICE_LEVEL_MONITOR_STATS	182
VTM_SERVICE_PROTECTION_STATS	183
VTM_CACHE_SSL_CACHE_STATS	185
VTM_SSL_OCSP_STAPLING_STATS	186
VTM_CACHE_SSL_SESSION_CACHE_STATS	187
VTM_TRAFFIC_IPS_TRAFFIC_IP_STATS	187
VTM_TRAFFIC_IPS_TRAFFIC_IP_INET46_STATS	188
VTM_CACHE_UNI_SESSION_CACHE_STATS	189
vtm_extras_user_counters_32_stats	190
vtm_extras_user_counters_64_stats	190
VTM_VIRTUAL_SERVER_STATS	190
VTM_CACHE_WEB_CACHE_STATS	197
System Information	199
VTM_BACKUPS_FULL	199
VTM_INFORMATION	200
VTM_STATE	200
Table Field Data Sources	202
EXAMPLE DEPLOYMENT TEMPLATE	205

# Preface

•	Document conventions	
•	Requesting Technical Support	-

# **Document conventions**

The document conventions describe text formatting conventions, command syntax conventions, and important notice formats used in Pulse Secure Secure technical documentation.

# **Text formatting conventions**

Text formatting conventions such as boldface, italic, or Courier font may be used in the flow of the text to highlight specific words or phrases.

Format	Description	
bold text	Identifies command names	
	Identifies keywords and operands	
	Identifies the names of user-manipulated GUI elements	
	Identifies text to enter at the GUI	
italic text	Identifies emphasis	
	Identifies variables	
	Identifies document titles	
Courier Font	Identifies command output	
	Identifies command syntax examples	

# Command syntax conventions

Bold and italic text identify command syntax components. Delimiters and operators define groupings of parameters and their logical relationships.

Convention	Description	
<b>bold text</b> Identifies command names, keywords, and command options.		
italic text	Identifies a variable.	
[]	Syntax components displayed within square brackets are optional.  Default responses to system prompts are enclosed in square brack	

Convention	Description	
{ x   y   z }	A choice of required parameters is enclosed in curly brackets separated by vertical bars. You must select one of the options.	
x   y	A vertical bar separates mutually exclusive elements.	
<>	Non-printing characters, for example, passwords, are enclosed in angle brackets.	
	Repeat the previous element, for example, member[member].	
\	Indicates a "soft" line break in command examples. If a backslash separates two lines of a command input, enter the entire command at the prompt without the backslash.	

### **Notes and Warnings**

Note, Attention, and Caution statements might be used in this document.

Note: A Note provides a tip, guidance, or advice, emphasizes important information, or provides a reference to related information.

#### ATTENTION

An Attention statement indicates a stronger note, for example, to alert you when traffic might be interrupted or the device might reboot.

#### CALITION

A Caution statement alerts you to situations that can be potentially hazardous to you or cause damage to hardware, firmware, software, or data.

# **Requesting Technical Support**

Technical product support is available through the Pulse Secure Global Support Center (PSGSC). If you have a support contract, file a ticket with PSGSC.

• Product warranties—For product warranty information, visit http://www.pulsesecure.net.

# Self-Help Online Tools and Resources

For quick and easy problem resolution, Pulse Secure, LLC has designed an online self-service portal called the Customer Support Center (CSC) that provides you with the following features:

- Find CSC offerings: https://www.pulsesecure.net/support
- Search for known bugs: https://www.pulsesecure.net/support
- Find product documentation: https://www.pulsesecure.net/techpubs
- Find solutions and answer questions using our Knowledge Center: https://www.pulsesecure.net/ support

- Download the latest versions of software and review release notes: https://www.pulsesecure.net/ support
- Search technical bulletins for relevant hardware and software notifications: https:// www.pulsesecure.net/support
- Open a case online in the CSC Case Management tool: https://www.pulsesecure.net/support
- To verify service entitlement by product serial number, use our Serial Number Entitlement (SNE) Tool: https://www.pulsesecure.net/support

# Opening a Case with PSGSC

You can open a case with PSGSC on the Web or by telephone.

- Use the Case Management tool in the PSGSC at https://www.pulsesecure.net/support.
- • Call 1-844 751 7629 (Toll Free, US).

For international or direct-dial options in countries without toll-free numbers, see https://www.pulsesecure.net/support.

# Overview

This chapter provides an overview of Pulse Secure Virtual Traffic Manager (the Traffic Manager). This chapter contains the following sections:

•	About This Guide	5
•	Introducing the Traffic Manager	5
•	Introducing the Terraform Provider	5

## **About This Guide**

The *Pulse Secure Virtual Traffic Manager: Terraform Provider Reference Guide* describes how to use the Terraform provider to create and configure Traffic Manager instance through deployment templates.

Read this guide for an introduction to the functionality available as part of the provider, for a complete reference to all Traffic Manager configuration resources and data sources, and for examples of how to use Terraform to provision your Traffic Manager deployment.

For a detailed description of the Traffic Manager and it's full feature set, see the *Pulse Secure Virtual Traffic Manager: User's Guide.* 

# Introducing the Traffic Manager

The Traffic Manager product family provides high-availability, application-centric traffic management and load balancing solutions in a range of software, hardware-ready, virtual appliance, and cloud-compute product variants. They provide control, intelligence, security and resilience for all your application traffic.

The Traffic Manager is intended for organizations hosting valuable business-critical services, such as TCP-based and UDP-based services like HTTP (web) and media delivery, and XML-based services such as Web Services.

# Introducing the Terraform Provider

Terraform is an open-source infrastructure-as-code tool produced by HashiCorp, Inc.

System administrators use Terraform to create and maintain configuration templates for your application infrastructure. Pulse Secure provides a set of tools to Terraform, known as a *provider*, that enable you to define Traffic Manager configurations within your application templates. Terraform can then provision Traffic Manager instances as part of a wider deployment.

To learn more about Terraform, see https://www.terraform.io.

# Getting Started

This chapter contains information about getting started using the Traffic Manager Terraform provider. This chapter contains the following sections:

•	Installing the Traffic Manager Terraform Provider	-
•	Initializing the Terraform Provider	-

# Installing the Traffic Manager Terraform Provider

To obtain the Pulse Secure Virtual Traffic Manager Terraform provider, download the source files from the *pulse-vadc* pages at GitHub:

https://github.com/pulse-vadc/terraform-provider-vtm

Make sure you download the version that corresponds to your target Traffic Manager's REST API version.

To install the provider in Terraform, follow the third-party plugin instructions at:

https://www.terraform.io/docs/configuration/providers.html#third-party-plugins

# Initializing the Terraform Provider

To use the Traffic Manager Terraform provider, initialize it within your Terraform template. The provider requires four arguments:

Field Name	Туре	Description
base_url	string	The base URL of the Traffic Manager REST API. Use either a direct Traffic Manager URL, or through a Pulse Secure Services Director (Services Director) proxy.
username	string	The admin username of either the Traffic Manager or the Services Director proxy you are connecting to.
password	string	The admin password of either the Traffic Manager or the Services Director proxy you are connecting to.
verify_ssl_cert	boolean	If set to true, the provider checks that the Traffic Manager/Services Director provides a trusted SSL certificate when connecting to the REST API. If set to false, untrusted (for example, self-signed) certificates are accepted. Default: true.

The following code provides examples of how to initialize the provider:

```
# Direct to the Traffic Manager
provider "vtm" {
   base_url = "https://192.0.2.10:9070/api"
```

```
username = "admin"
  password = "mYvtm53cret!"
  verify_ssl_cert = true
}

# Through a Services Director proxy
provider "vtm" {
  base_url = "https://192.0.2.100:8100/api/tmcm/<VERSION>/instance/<INSTANCE_ID>"
  username = "admin"
  password = "mYsd53cret!"
  verify_ssl_cert = true
}
```

# Resource and Data Source Reference

This chapter introduces the resource model, demonstrates it's usage through the provider, and includes a complete listing of all available Traffic Manager configuration resources and data sources. This chapter contains the following sections:

•	About the Resource Model	S
•	Using the Resource Model	9
•	Configuration Resources	10
•	Data Sources	48

#### About the Resource Model

The resource model reference included in this chapter lists all configuration resources and data sources available through the Traffic Manager REST API. Each sub-section relates to a specific resource type or data source, showing its name, description, unique URI path, and a table of properties.

Each property contains a description and data type. Additional information is provided where applicable, such as default value and permitted values (for enumerated types). For Table-type properties, a list of the Primary and Sub keys is provided.

For configuration resources, each property, and table keys where applicable, include an indicator of whether or not that item is a required value when creating configuration based on that resource.

For further information concerning the Traffic Manager REST API, see the *Pulse Secure Virtual Traffic Manager: REST API Guide*, available from the Pulse Secure website.

# Using the Resource Model

Resources can represent objects of a singular nature (for example, global settings) where only one instance of that resource type is ever present, or collections of objects (for example, virtual servers) where multiple instances might be created. To uniquely identify a specific instance of a collection-type resource, use the "name" property. Resources of a singular type do not require the "name" property.

Furthermore, there are two types of collection:

- Key/value resources. For example, virtual servers.
- · Raw text files. For example, TrafficScript rules

Key/value resources have unique data structures, as defined in the resource model reference, whereas raw file resources have only two parameters; "name" and "content".

#### **ATTENTION**

Pulse Secure strongly recommends that singular object resources are only specified in one template for any cluster. Specifying these resources in multiple templates can lead to altering cluster-wide settings that impact other services.

# **Configuration Resources**

Configuration resources map to objects in the Traffic Manager's configuration system. The Terraform provider uses these resource definitions to provision services hosted on your Traffic Manager instances.

# Setting Configuration Values Using the Resource Model

The following code samples show how to set configuration properties for different resource types:

```
# Single object configuration
resource "vtm global settings" "global settings" {
   admin support tls1 = false
   connection idle timeout = 30
# Collection-type key/value object configuration
resource "vtm pool" "my pool" {
   name = "MyPool"
   monitors = ["Ping", "Simple HTTP"]
   load_balancing_algorithm = "weighted_least_connections"
   nodes table {
     node = "192.0.2.101:80"
      weight = 1
   nodes table {
     node = "192.0.2.102:80"
     weight = 3
   nodes table {
     node = "192.0.2.103:80"
      weight = 3
      state = "disabled"
}
# Collection-type raw text object configuration
resource "vtm rule" "my rule" {
  name = "MyRule"
   content = << EOF
$hostHeader = http.getHostHeader();
if($hostHeader == "www.example.com") {
   pool.use("ExamplePool");
}
EOF
```

Dependancy Tree

}

Generally speaking, the Traffic Manager REST API is tolerant of objects being created out-of-order. In other words, the REST API allows you to create a virtual server that references a TrafficScript rule that does not yet exist, even though this would trigger an error in the Traffic Manager diagnostics and event log. This error is suppressed after the corresponding rule is subsequently added. However, there are exceptions to this arrangement.

Pulse Secure recommends that all resource dependencies are explicitly specified by using parameter interpolation when creating relationships, rather than hard-coding names. For example, rather than providing a list of rule names to a virtual server as strings, specify the names as variables to aid Terraform in building the correct dependancy tree. The following code samples demonstrate this process.

The code sample below shows the partial configuration of a virtual server with named request rules:

```
resource "vtm_virtual_server" "example" {
   name = "ExampleVS"
   request_rules = ["rule1", "rule2"]
   ...
}
```

Rather than specifying the hard-coded strings "rule1" and "rule2" in the list of request rules, use instead a set of variables to provide the rule names. The following code sample demonstrates the syntax used to reference properties of other resource objects in the provider:

```
resource "vtm_virtual_server" "example" {
   name = "ExampleVS"
   request_rules = ["${vtm_rule.rule1.name}", "${vtm_rule.rule2.name}"]
   ...
}
```

#### Resource Reference

Use the configuration resource definitions in this section to provision services on your Traffic Manager instances.

# vtm\_action\_program

URI Endpoint: /api/tm/4.0/config/active/action\_programs

This is a program or script that can be referenced and used by actions of type 'Program'

```
# Example usage of vtm_action_program resource...
resource "vtm_action_program" "my_action_program" {
    content = ""
    name = "MyActionProgram"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
content	Object content
	<ul><li>Type: string</li><li>Required: true</li></ul>

## vtm\_action

URI Endpoint: /api/tm/4.0/config/active/actions

A response to an event occurring in your traffic manager. An example of an action might be sending an email or writing a line to a log file.

```
# Example usage of vtm_action resource...
resource "vtm_action" "my_action" {
    name = "MyAction"
    type =
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
email_server	The SMTP server to which messages should be sent. This must be a valid IPv4 address or resolvable hostname (with optional port).
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
email_to	A set of e-mail addresses to which messages will be sent.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
log_file	The full path of the file to log to. The text %zeushome% will be replaced with the location where the software is installed.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
log_from	The e-mail address from which messages will appear to originate.  • Type: String  • Required: false  • Default value: "vTM@%hostname%"

Property	Description
note	A description of the action.  • Type: FreeformString
	<ul><li>Required: false</li><li>Default value: <none></none></li></ul>
program_arguments	A table containing arguments and argument values to be passed to the event handling program.  Type: Table
	<ul> <li>Required: false</li> <li>Primary key:         <ul> <li>name (String): The name of the argument to be passed to the event handling program. (Required)</li> </ul> </li> <li>Sub keys:</li> </ul>
	<ul> <li>value (String): The value of the argument to be passed to the event handling program.</li> <li>description (String): A description for the argument provided to the program.</li> </ul>
program_arguments_json	A Traffic Manager REST-compatible JSON representation of the "program_arguments" table property. Use this field with the "vtm_action_arguments_table" data source for dynamic table generation from input variables.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
program_program	The program to run.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
soap_additional_data	Additional information to send with the SOAP call.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
soap_password	The password for HTTP basic authentication.
	<ul><li>Type: Password</li><li>Required: false</li><li>Default value: <none></none></li></ul>
soap_proxy	The address of the server implementing the SOAP interface (For example, https://example.com).
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
soap_username	Username for HTTP basic authentication. Leave blank if you do not wish to use authentication.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
syslog_msg_len_limit	Maximum length in bytes of a message sent to the remote syslog.  Messages longer than this will be truncated before they are sent.  Type: UInt Required: false Default value: "1024"
syslog_sysloghost	The host and optional port to send syslog messages to (if empty, messages will be sent to localhost).  Type: String
timeout	<ul> <li>Required: false</li> <li>Default value: <none></none></li> <li>How long the action can run for before it is stopped automatically (set</li> </ul>
timeout	to 0 to disable timeouts).  Type: UInt Required: false Default value: "60"
trap_auth_password	The authentication password for sending a Notify over SNMPv3. Blank to send unauthenticated traps.  Type: Password Required: false Default value: <none></none>
trap_community	The community string to use when sending a Trap over SNMPv1 or a Notify over SNMPv2c.  Type: String Required: false Default value: <none></none>
trap_hash_algorithm	The hash algorithm for SNMPv3 authentication.  Type: Enum(String) Required: false Default value: "md5" Permitted values: "md5": MD5 "sha1": SHA-1
trap_priv_password	The encryption password to encrypt a Notify message for SNMPv3. Requires that authentication also be configured. Blank to send unencrypted traps.  Type: Password Required: false Default value: <none></none>
trap_traphost	The hostname or IPv4 address and optional port number that should receive traps.  Type: String Required: false Default value: <none></none>

Property	Description
trap_username	The SNMP username to use to send the Notify over SNMPv3.  • Type: String  • Required: false  • Default value: <none></none>
trap_version	The SNMP version to use to send the Trap/Notify.  Type: Enum(String) Required: false Default value: "snmpv1" Permitted values: "snmpv1": SNMPv1 "snmpv2c": SNMPv2c "snmpv3": SNMPv3
type	The action type.  Type: Enum(String) Required: true Default value: <none> Permitted values: "email": E-Mail "log": Log to File "program": Program "soap": SOAP Callback "syslog": Log to Syslog "trap": SNMP Notify or Trap</none>
verbose	Enable or disable verbose logging for this action.  Type: Boolean Required: false Default value: false

## vtm\_aptimizer\_scope

URI Endpoint: /api/tm/4.0/config/active/aptimizer/scopes

Application scopes define criteria that match URLs to specific logical web applications hosted by a virtual server.

```
# Example usage of vtm_aptimizer_scope resource...
resource "vtm_aptimizer_scope" "my_aptimizer_scope" {
    name = "MyAptimizerScope"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
canonical_hostname	If the hostnames for this scope are aliases of each other, the canonical hostname will be used for requests to the server.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
hostnames	The hostnames to limit acceleration to.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
root	The root path of the application defined by this application scope.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "/"</li></ul>

### vtm\_bgpneighbor

URI Endpoint: /api/tm/4.0/config/active/bgpneighbors

The conf/bgpneighbors directory contains configuration files for BGP neighbors. The name of a file is the name of the neighbor configuration that it defines. BGP neighbors can be managed under the System > Fault Tolerance > BGP Neighbors section of the Admin UI, or by using functions under the BGPNeighbors section of the SOAP API and CLI.

```
# Example usage of vtm_bgpneighbor resource...
resource "vtm_bgpneighbor" "my_bgpneighbor" {
    name = "MyBgpneighbor"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
address	The IP address of the BGP neighbor
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
advertisement_interval	The minimum interval between the sending of BGP routing updates to neighbors. Note that as a result of jitter, as defined for BGP, the interval during which no advertisements are sent will be between 75% and 100% of this value.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "5"</li></ul>
as_number	The AS number for the BGP neighbor
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "65534"</li></ul>
authentication_password	The password to be used for authentication of sessions with neighbors
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
holdtime	The period after which the BGP session with the neighbor is deemed to have become idle - and requires re-establishment - if the neighbor falls silent.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "90"</li></ul>
keepalive	The interval at which messages are sent to the BGP neighbor to keep the mutual BGP session established.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "30"</li></ul>
machines	The traffic managers that are to use this neighbor
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>

## vtm\_bandwidth

URI Endpoint: /api/tm/4.0/config/active/bandwidth

A Bandwidth class, which can be assigned to a virtual server or pool in order to limit the number of bytes per second used by inbound or outbound traffic.

```
# Example usage of vtm_bandwidth resource...
resource "vtm_bandwidth" "my_bandwidth" {
    name = "MyBandwidth"
}
```

Property	Description
name	Name of the object  Type: string Required: true
maximum	The maximum bandwidth to allocate to connections that are associated with this bandwidth class (in kbits/second).  Type: Ulnt Required: false Default value: "10000"
note	A description of this bandwidth class.  Type: FreeformString Required: false Default value: <none></none>
sharing	<ul> <li>The scope of the bandwidth class.</li> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "cluster"</li> <li>Permitted values:     "cluster": Bandwidth is shared across all traffic managers     "connection": Each connection can use the maximum rate     "machine": Bandwidth is shared per traffic manager</li> </ul>

### vtm\_application\_firewall

URI Endpoint: /api/tm/4.0/config/active/application\_firewall

The conf/zeusafm.conf file contains configuration files for the application firewall. Some keys present in the zeusafm.conf are not documented here. Refer to the Brocade Virtual Web Application Firewall documentation for further details. The configuration can be edited under the System > Application Firewall section of the Administration Server or by using functions under the AFM section of the SOAP API and CLI.

Property	Description
There are no properties to display for this resource.	

# vtm\_cloud\_api\_credential

 $URI\ Endpoint: \ /api/tm/4.0/config/active/cloud\_api\_credentials$ 

Cloud credentials used in cloud API calls

```
# Example usage of vtm_cloud_api_credential resource...
resource "vtm_cloud_api_credential" "my_cloud_api_credential" {
    name = "MyCloudApiCredential"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
api_server	The vCenter server hostname or IP address.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
cloud_api_timeout	The traffic manager creates and destroys nodes via API calls. This setting specifies (in seconds) how long to wait for such calls to complete.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "200"</li></ul>
cred1	The first part of the credentials for the cloud user. Typically this is some variation on the username concept.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
cred2	The second part of the credentials for the cloud user. Typically this is some variation on the password concept.
	<ul><li>Type: Password</li><li>Required: false</li><li>Default value: <none></none></li></ul>
cred3	The third part of the credentials for the cloud user. Typically this is some variation on the authentication token concept.
	<ul><li>Type: Password</li><li>Required: false</li><li>Default value: <none></none></li></ul>
script	The script to call for communication with the cloud API.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
update_interval	The traffic manager will periodically check the status of the cloud through an API call. This setting specifies the interval between such updates.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "30"</li></ul>

#### vtm\_custom

URI Endpoint: /api/tm/4.0/config/active/custom

Custom configuration sets store arbitrary named values. These values can be read by SOAP or REST clients.

```
# Example usage of vtm_custom resource...
resource "vtm_custom" "my_custom" {
    name = "MyCustom"
}
```

Property	Description
name	Name of the object  Type: string Required: true
string_lists	<ul> <li>This table contains named lists of strings</li> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>name (String): Name of list (Required)</li> </ul> </li> <li>Sub keys: <ul> <li>value (List(String)): Named list of user-specified strings.</li> </ul> </li> </ul>
string_lists_json	A Traffic Manager REST-compatible JSON representation of the "string_lists" table property. Use this field with the "vtm_custom_string_lists_table" data source for dynamic table generation from input variables.  Type: String Required: false Default value: <none></none>

# vtm\_dns\_server\_zone

URI Endpoint: /api/tm/4.0/config/active/dns\_server/zones

The conf/dnsserver/zones/ file contains zone metadata

```
# Example usage of vtm_dns_server_zone resource...
resource "vtm_dns_server_zone" "my_dns_server_zone" {
   name = "MyDnsServerZone"
   origin =
   zonefile =
}
```

Property	Description
name	Name of the object Type: string Required: true
origin	The domain origin of this Zone.  Type: String Required: true Default value: <none></none>
zonefile	The Zone File encapsulated by this Zone.  Type: String Required: true Default value: <none></none>

#### vtm\_dns\_server\_zone\_file

URI Endpoint: /api/tm/4.0/config/active/dns\_server/zone\_files

The conf/dnsserver/zonefiles/ directory contains files that define DNS zones.

```
# Example usage of vtm_dns_server_zone_file resource...
resource "vtm_dns_server_zone_file" "my_dns_server_zone_file" {
    content = ""
    name = "MyDnsServerZoneFile"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
content	Object content
	<ul><li>Type: string</li><li>Required: true</li></ul>

#### vtm\_event\_type

URI Endpoint: /api/tm/4.0/config/active/event\_types

Configuration that ties actions to a set of events that trigger them.

```
# Example usage of vtm_event_type resource...
resource "vtm_event_type" "my_event_type" {
    name = "MyEventType"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
actions	The actions triggered by events matching this event type, as a list of action references.
	<ul><li>Type: List(Reference(config-event-action))</li><li>Required: false</li><li>Default value: <none></none></li></ul>
built_in	If set to Yes this indicates that this configuration is built-in (provided as part of the software) and must not be deleted or edited.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
cloudcredentials_event_tags	Cloud credentials event tags
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
cloudcredentials_objects	Cloud credentials object names
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
config_event_tags	Configuration file event tags
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
faulttolerance_event_tags	Fault tolerance event tags
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
general_event_tags	General event tags
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
glb_event_tags	GLB service event tags
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
glb_objects	GLB service object names  Type: List(String) Required: false Default value: <none></none>

Property	Description
java_event_tags	Java event tags  Type: List(String) Required: false Default value: <none></none>
licensekeys_event_tags	License key event tags  Type: List(String) Required: false Default value: <none></none>
licensekeys_objects	License key object names  Type: List(String) Required: false Default value: <none></none>
locations_event_tags	Location event tags  Type: List(String) Required: false Default value: <none></none>
locations_objects	Location object names  Type: List(String) Required: false Default value: <none></none>
monitors_event_tags	Monitor event tags  Type: List(String) Required: false Default value: <none></none>
monitors_objects	Monitors object names  Type: List(String) Required: false Default value: <none></none>
note	<ul> <li>A description of this event type.</li> <li>Type: FreeformString</li> <li>Required: false</li> <li>Default value: <none></none></li> </ul>
pools_event_tags	Pool key event tags  Type: List(String) Required: false Default value: <none></none>
pools_objects	Pool object names  Type: List(String) Required: false Default value: <none></none>

Property	Description
protection_event_tags	Service protection class event tags  Type: List(String) Required: false Default value: <none></none>
protection_objects	Service protection class object names  Type: List(String) Required: false Default value: <none></none>
rules_event_tags	Rule event tags  Type: List(String) Required: false Default value: <none></none>
rules_objects	Rule object names  Type: List(String) Required: false Default value: <none></none>
slm_event_tags	SLM class event tags  Type: List(String) Required: false Default value: <none></none>
slm_objects	SLM class object names  Type: List(String) Required: false Default value: <none></none>
ssl_event_tags	SSL event tags  Type: List(String) Required: false Default value: <none></none>
sslhw_event_tags	SSL hardware event tags  Type: List(String) Required: false Default value: <none></none>
trafficscript_event_tags	TrafficScript event tags  Type: List(String) Required: false Default value: <none></none>
vservers_event_tags	Virtual server event tags  Type: List(String) Required: false Default value: <none></none>

Property	Description
vservers_objects	Virtual server object names
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
zxtms_event_tags	Traffic manager event tags
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
zxtms_objects	Traffic manager object names
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>

## vtm\_extra\_file

URI Endpoint: /api/tm/4.0/config/active/extra\_files

A user-uploaded file. Such files can be used in TrafficScript code using the resource.get function.

```
# Example usage of vtm_extra_file resource...
resource "vtm_extra_file" "my_extra_file" {
    content = ""
    name = "MyExtraFile"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
content	Object content
	<ul><li>Type: string</li><li>Required: true</li></ul>

### vtm\_glb\_service

URI Endpoint: /api/tm/4.0/config/active/glb\_services

A global load balancing service is used by a virtual server to modify DNS requests in order load balance data across different GLB locations.

```
# Example usage of vtm_glb_service resource...
resource "vtm_glb_service" "my_glb_service" {
    name = "MyGlbService"
}
```

Property	Description
name	Name of the object  Type: string Required: true
algorithm	Defines the global load balancing algorithm to be used.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "hybrid"</li> <li>Permitted values:     "chained": Sends traffic to one location at a time, until that location fails where the next one in the chain is used.</li> </ul>
	"geo": Distributes traffic based solely on the geographic location of each client.
	"hybrid": Distribute traffic based on both the load and geographic location.
	"load": Distributes traffic based on the current load to each location.
	"round_robin": Distributes traffic by assigning each request to a new location in turn. Over a period of time, all locations will receive the same number of requests.
	"weighted_random": Distributes traffic in a random way, but according to a weighted policy defined by individual location weights
all_monitors_needed	Are all the monitors required to be working in a location to mark this service as alive?
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
autorecovery	The last location to fail will be available as soon as it recovers.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
chained_auto_failback	Enable/Disable automatic failback mode.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
chained_location_order	The locations this service operates for and defines the order in which locations fail.
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
disable_on_failure	Locations recovering from a failure will become disabled.  Type: Boolean Required: false Default value: false
dnssec_keys	<ul> <li>A table mapping domains to the private keys that authenticate them</li> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>domain (String): A domain authenticated by the associated private keys. (Required)</li> </ul> </li> <li>Sub keys: <ul> <li>ssl_key (Set(String)): Private keys that authenticate the associated domain.</li> </ul> </li> </ul>
dnssec_keys_json	A Traffic Manager REST-compatible JSON representation of the "dnssec_keys" table property. Use this field with the "vtm_glb_service_dnssec_keys_table" data source for dynamic table generation from input variables.  • Type: String • Required: false • Default value: <none></none>
domains	The domains shown here should be a list of Fully Qualified Domain Names that you would like to balance globally. Responses from the back end DNS servers for queries that do not match this list will be forwarded to the client unmodified. Note: "*" may be used as a wild card.  • Type: Set(String)  • Required: false  • Default value: <none></none>
enabled	<ul> <li>Enable/Disable our response manipulation of DNS.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
geo_effect	How much should the locality of visitors affect the choice of location used? This value is a percentage, 0% means that no locality information will be used, and 100% means that locality will always control which location is used. Values between the two extremes will act accordingly.  Type: Ulnt Required: false Default value: "50"
last_resort_response	The response to be sent in case there are no locations available.  Type: Set(String) Required: false Default value: <none></none>

Property	Description
location_draining	This is the list of locations for which this service is draining. A location that is draining will never serve any of its service IP addresses for this domain. This can be used to take a location off-line.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
location_settings	Table containing location specific settings.
	<ul> <li>Type: Table</li> <li>Required: false</li> <li>Primary key:         <ul> <li>location (String): Location to which the associated settings apply. (Required)</li> </ul> </li> <li>Sub keys:         <ul> <li>weight (UInt): Weight for this location, for use by the weighted random algorithm.</li> <li>ips (Set(String)): The IP addresses that are present in a location.</li> </ul> </li> </ul>
	If the Global Load Balancer decides to direct a DNS query to this location, then it will filter out all IPs that are not in this list.  - monitors (Set(String)): The monitors that are present in a location.
location_settings_json	A Traffic Manager REST-compatible JSON representation of the "location_settings" table property. Use this field with the "vtm_glb_service_location_settings_table" data source for dynamic table generation from input variables.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
log_enabled	Log connections to this GLB service?
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
log_filename	The filename the verbose query information should be logged to. Appliances will ignore this.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "%zeushome%/zxtm/log/services/%g.log"</li></ul>
log_format	The format of the log lines.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "%t, %s, %l, %q, %g, %n, %d, %a"</li></ul>
return_ips_on_fail	Return all or none of the IPs under complete failure.  Type: Boolean Required: false Default value: false

Property	Description
rules	Response rules to be applied in the context of the service, in order, comma separated.
	<ul><li>Type: List(Reference(config-trafficscript))</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ttl	The TTL for the DNS resource records handled by the GLB service.
	<ul><li>Type: Int</li><li>Required: false</li><li>Default value: "-1"</li></ul>

# vtm\_global\_settings

URI Endpoint: /api/tm/4.0/config/active/global\_settings

General settings that apply to every machine in the cluster.

```
# Example usage of vtm_global_settings resource...
resource "vtm_global_settings" "my_global_settings" {
}
```

Property	Description
accepting_delay	How often, in milliseconds, each traffic manager child process (that isn't listening for new connections) checks to see whether it should start listening for new connections.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "50"</li></ul>
admin_honor_fallback_scsv	Whether or not the admin server, the internal control port and the config daemon honor the Fallback SCSV to protect connections against downgrade attacks.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
admin_ssl3_allow_rehandshak e	Whether or not SSL3/TLS re-handshakes should be supported for admin server and internal connections.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "rfc5746"</li> <li>Permitted values: "always": Always allow</li> </ul>
	"never": Never allow
	"rfc5746": Only if client uses RFC 5746 (Secure Renegotiation Extension)
	"safe": Allow safe re-handshakes

Property	Description
admin_ssl3_ciphers	The SSL ciphers to use for admin server and internal connections. For information on supported ciphers see the online help.
	<ul> <li>Type: String</li> <li>Required: false</li> <li>Default value:  "SSL_RSA_WITH_AES_128_GCM_SHA256,SSL_RSA_WITH_AES_128_C BC_SHA256,SSL_RSA_WITH_AES_128_CBC_SHA,SSL_RSA_WITH_AES _256_GCM_SHA384,SSL_RSA_WITH_AES_256_CBC_SHA256,SSL_RS A_WITH_AES_256_CBC_SHA,SSL_RSA_WITH_3DES_EDE_CBC_SHA,S SL_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256,SSL_ECDHE_ECD SA_WITH_AES_256_GCM_SHA384,SSL_ECDHE_ECDSA_WITH_AES_1 28_CBC_SHA,SSL_DHE_DSS_WITH_AES_128_CBC_SHA,SSL_DHE_DS S_WITH_AES_256_CBC_SHA,SSL_DHE_DSS_WITH_3DES_EDE_CBC_S HA"</li> </ul>
admin_ssl3_diffie_hellman_key _length	The length in bits of the Diffie-Hellman key for ciphers that use Diffie-Hellman key agreement for admin server and internal connections.
	<ul> <li>Type: Enum(UInt)</li> <li>Required: false</li> <li>Default value: "dh_2048"</li> <li>Permitted values:     "dh_1024": Use 1024 bit keys for Diffie-Hellman ciphers.</li> </ul>
	"dh_2048": Use 2048 bit keys for Diffie-Hellman ciphers.
	"dh_3072": Use 3072 bit keys for Diffie-Hellman ciphers.
	"dh_4096": Use 4096 bit keys for Diffie-Hellman ciphers.
admin_ssl3_min_rehandshake _interval	If SSL3/TLS re-handshakes are supported on the admin server, this defines the minimum time interval (in milliseconds) between handshakes on a single SSL3/TLS connection that is permitted. To disable the minimum interval for handshakes the key should be set to the value 0.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "1000"</li></ul>
admin_ssl_elliptic_curves	The SSL elliptic curve preference list for admin and internal connections. The named curves P256, P384 and P521 may be configured.
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
admin_ssl_insert_extra_fragme nt	<ul> <li>Whether or not SSL3 and TLS1 use one-byte fragments as a BEAST countermeasure for admin server and internal connections.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>

Property	Description
admin_ssl_max_handshake_m essage_size	The maximum size (in bytes) of SSL handshake messages that the admin server and internal connections will accept. To accept any size of handshake message the key should be set to the value 0.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10240"</li></ul>
admin_ssl_prevent_timing_sid e_channels	Take performance degrading steps to prevent exposing timing side- channels with SSL3 and TLS used by the admin server and internal connections.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
admin_ssl_signature_algorith ms	The SSL signature algorithms preference list for admin and internal connections using TLS version 1.2 or higher. For information on supported algorithms see the online help.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
admin_support_ssl2	No longer supported. Formerly controlled whether SSLv2 could be used for connections to the Administration Server.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
admin_support_ssl3	Whether or not SSL3 support is enabled for admin server and internal connections.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
admin_support_tls1	Whether or not TLS1.0 support is enabled for admin server and internal connections.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
admin_support_tls11	Whether or not TLS1.1 support is enabled for admin server and internal connections.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
admin_support_tls12	Whether or not TLS1.2 support is enabled for admin server and internal connections.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

Property	Description
afm_enabled	Is the application firewall enabled.  Type: Boolean Required: false Default value: false
appliance_bootloader_password	The password used to protect the bootloader. An empty string means there will be no protection.  Type: Password Required: false Default value: <none></none>
appliance_manage_ncipher	Whether or not we should manage the nCipher Support Software automatically.  Type: Boolean Required: false Default value: false
appliance_nethsm_esn	The ESN (electronic serial number) for the NetHSM.  Type: String Required: false Default value: <none></none>
appliance_nethsm_hash	The key hash for the NetHSM.  Type: String Required: false Default value: <none></none>
appliance_nethsm_ip	The IP address of the nCipher NetHSM to use.  • Type: String • Required: false • Default value: <none></none>
appliance_nethsm_ncipher_rfs	The IP address of the nCipher Remote File System to use.  • Type: String  • Required: false  • Default value: <none></none>
appliance_return_path_routin g_enabled	Whether or not the traffic manager will attempt to route response packets back to clients via the same route on which the corresponding request arrived. Note that this applies only to the last hop of the route - the behaviour of upstream routers cannot be altered by the traffic manager.  Type: Boolean Required: false Default value: false

Property	Description
aptimizer_max_dependent_fet ch_size	The maximum size of a dependent resource that can undergo Web Accelerator optimization. Any content larger than this size will not be optimized. Units of KB and MB can be used, no postfix denotes bytes. A value of 0 disables the limit.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "2MB"</li></ul>
aptimizer_max_original_conte nt_buffer_size	The maximum size of unoptimized content buffered in the traffic manager for a single backend response that is undergoing Web Accelerator optimization. Responses larger than this will not be optimized. Note that if the backend response is compressed then this setting pertains to the compressed size, before Web Accelerator decompresses it. Units of KB and MB can be used, no postfix denotes bytes. Value range is 1 - 128MB.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "2MB"</li></ul>
aptimizer_watchdog_interval	The period of time (in seconds) after which a previous failure will no longer count towards the watchdog limit.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "300"</li></ul>
aptimizer_watchdog_limit	The maximum number of times the Web Accelerator sub-process will be started or restarted within the interval defined by the aptimizer!watchdog_interval setting. If the process fails this many times, it must be restarted manually from the Diagnose page. Zero means no limit.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "3"</li></ul>
auditlog_via_eventd	Whether to mirror the audit log to EventD.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
auditlog_via_syslog	Whether to output audit log message to the syslog.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
autoscaler_verbose	Whether or not detailed messages about the autoscaler's activity are written to the error log.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

Property	Description
bgp_as_number	The number of the BGP AS in which the traffic manager will operate. Must be entered in decimal.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "65534"</li></ul>
bgp_enabled	Whether BGP Route Health Injection is enabled
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
chunk_size	The default chunk size for reading/writing requests.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "16384"</li></ul>
client_first_opt	Whether or not your traffic manager should make use of TCP optimisations to defer the processing of new client-first connections until the client has sent some data.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
cluster_comms_allow_update_default	The default value of allow_update for new cluster members. If you have cluster members joining from less trusted locations (such as cloud instances) this can be set to false in order to make them effectively "read-only" cluster members.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
cluster_comms_allowed_upda te_hosts	The hosts that can contact the internal administration port on each traffic manager. This should be a list containing IP addresses, CIDR IP subnets, and localhost; or it can be set to all to allow any host to connect.
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: "all"</li></ul>
cluster_comms_state_sync_int erval	How often to propagate the session persistence and bandwidth information to other traffic managers in the same cluster. Set this to 0 (zero) to disable propagation. Note that a cluster using "unicast" heartbeat messages cannot turn off these messages.  Type: Ulnt Required: false Default value: "3"

Property	Description
cluster_comms_state_sync_ti meout	The maximum amount of time to wait when propagating session persistence and bandwidth information to other traffic managers in the same cluster. Once this timeout is hit the transfer is aborted and a new connection created.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "6"</li></ul>
cluster_identifier	Cluster identifier. Generally supplied by Services Director.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
connection_idle_connections_ max	The maximum number of unused HTTP keepalive connections with back-end nodes that the traffic manager should maintain for re-use. Setting this to 0 (zero) will cause the traffic manager to auto-size this parameter based on the available number of file-descriptors.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
connection_idle_timeout	How long an unused HTTP keepalive connection should be kept before it is discarded.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>
connection_listen_queue_size	The listen queue size for managing incoming connections. It may be necessary to increase the system's listen queue size if this value is altered. If the value is set to 0 then the default system setting will be used.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
connection_max_accepting	Number of processes that should accept new connections. Only this many traffic manager child processes will listen for new connections at any one time. Setting this to 0 (zero) will cause your traffic manager to select an appropriate default value based on the architecture and number of CPUs.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
connection_multiple_accept	Whether or not the traffic manager should try to read multiple new connections each time a new client connects. This can improve performance under some very specific conditions. However, in general it is recommended that this be set to 'false'.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

Property	Description
data_plane_acceleration_cores	The number of CPU cores assigned to assist with data plane acceleration. These cores are dedicated to reading and writing packets to the network interface cards and distributing packets between the traffic manager processes.
	<ul> <li>Type: Enum(UInt)</li> <li>Required: false</li> <li>Default value: "one"</li> <li>Permitted values: "four": 4</li> </ul>
	"one": 1 "two": 2
data_plane_acceleration_mod	Whether Data Plane Acceleration Mode is enabled.
e	<ul> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
data_plane_acceleration_tcp_d elay_ack	The time, in milliseconds, to delay sending a TCP ACK response, providing an opportunity for additional data to be incorporated into the response and potentially improving network performance. The setting affects TCP connections handled by layer 7 services running in Data Plane Acceleration mode.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "200"</li></ul>
data_plane_acceleration_tcp_ win_scale	The TCP window scale option, which configures the size of the receive window for TCP connections handled by layer 7 services when running in Data Plane Acceleration mode.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "7"</li></ul>
dns_max_ttl	Maximum Time To Live (expiry time) for entries in the DNS cache.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "86400"</li></ul>
dns_min_ttl	Minimum Time To Live (expiry time) for entries in the DNS cache.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "86400"</li></ul>
dns_negative_expiry	<ul> <li>Expiry time for failed lookups in the DNS cache.</li> <li>Type: UInt</li> <li>Required: false</li> <li>Default value: "60"</li> </ul>

Property	Description
dns_size	Maximum number of entries in the DNS cache.  Type: UInt Required: false Default value: "10867"
dns_timeout	Timeout for receiving a response from a DNS server.  Type: UInt Required: false Default value: "12"
ec2_access_key_id	Amazon EC2 Access Key ID.  Type: String Required: false Default value: <none></none>
ec2_awstool_timeout	The maximum amount of time requests to the AWS Query API can take before timing out.  Type: UInt Required: false Default value: "10"
ec2_secret_access_key	Amazon EC2 Secret Access Key.  Type: Password Required: false Default value: <none></none>
ec2_verify_query_server_cert	Whether to verify Amazon EC2 endpoint's certificate using CA(s) present in SSL Certificate Authorities Catalog.  Type: Boolean Required: false Default value: false
eventing_mail_interval	The minimum length of time that must elapse between alert emails being sent. Where multiple alerts occur inside this timeframe, they will be retained and sent within a single email rather than separately.  Type: Ulnt Required: false Default value: "30"
eventing_max_attempts	The number of times to attempt to send an alert email before giving up.  Type: UInt Required: false Default value: "10"
fault_tolerance_arp_count	The number of ARP packets a traffic manager should send when an IP address is raised.  Type: UInt Required: false Default value: "10"

Property	Description
fault_tolerance_auto_failback	Whether or not traffic IPs automatically move back to machines that have recovered from a failure and have dropped their traffic IPs.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
fault_tolerance_autofailback_d elay	Configure the delay of automatic failback after a previous failover event. This setting has no effect if autofailback is disabled.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>
fault_tolerance_child_timeout	How long the traffic manager should wait for status updates from any of the traffic manager's child processes before assuming one of them is no longer servicing traffic.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "5"</li></ul>
fault_tolerance_frontend_check_ips	The IP addresses used to check front-end connectivity. The text %gateway% will be replaced with the default gateway on each system. Set this to an empty string if the traffic manager is on an Intranet with no external connectivity.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: "%gateway%"</li></ul>
fault_tolerance_heartbeat_met hod	The method traffic managers should use to exchange cluster heartbeat messages.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "unicast"</li> <li>Permitted values: "multicast": multicast</li> </ul>
	"unicast": unicast
fault_tolerance_igmp_interval	The interval between unsolicited periodic IGMP Membership Report messages for Multi-Hosted Traffic IP Groups.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "30"</li></ul>
fault_tolerance_l4accel_child_ti meout	When running in Data Plane Acceleration Mode, how long the traffic manager should wait for a status update from child processes handling L4Accel services before assuming it is no longer servicing traffic.  Type: Ulnt
	<ul> <li>Required: false</li> <li>Default value: "2"</li> </ul>

Property	Description
fault_tolerance_l4accel_sync_p ort	The port on which cluster members will transfer state information for L4Accel services when running in Data Plane Acceleration Mode.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "10240"</li></ul>
fault_tolerance_monitor_interv al	The frequency, in milliseconds, that each traffic manager machine should check and announce its connectivity.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "500"</li></ul>
fault_tolerance_monitor_timeo ut	How long, in seconds, each traffic manager should wait for a response from its connectivity tests or from other traffic manager machines before registering a failure.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "5"</li></ul>
fault_tolerance_multicast_addr ess	The multicast address and port to use to exchange cluster heartbeat messages.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "239.100.1.1:9090"</li></ul>
fault_tolerance_unicast_port	The unicast UDP port to use to exchange cluster heartbeat messages.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "9090"</li></ul>
fault_tolerance_use_bind_ip	Whether or not cluster heartbeat messages should only be sent and received over the management network.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
fault_tolerance_verbose	Whether or not a traffic manager should log all connectivity tests. This is very verbose, and should only be used for diagnostic purposes.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
fips_enabled	Enable FIPS Mode (requires software restart).
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

Property	Description
ftp_data_bind_low	Whether or not the traffic manager should permit use of FTP data connection source ports lower than 1024. If No the traffic manager can completely drop root privileges, if Yes some or all privileges may be retained in order to bind to low ports.  Type: Boolean Required: false Default value: false
glb_verbose	Write a message to the logs for every DNS query that is load balanced, showing the source IP address and the chosen datacenter.  Type: Boolean Required: false Default value: false
historical_activity_keep_days	Number of days to store historical traffic information, if set to 0 the data will be kept indefinitely.  Type: UInt Required: false Default value: "90"
ip_appliance_returnpath	<ul> <li>A table of MAC to IP address mappings for each router where return path routing is required.</li> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>mac (String): The MAC address of a router the software is connected to. (Required)</li> </ul> </li> <li>Sub keys: <ul> <li>ipv4 (String): The MAC address to IPv4 address mapping of a router the software is connected to. The * (asterisk) in the key name is the MAC address, the value is the IP address.</li> <li>ipv6 (String): The MAC address to IPv6 address mapping of a router the software is connected to. The * (asterisk) in the key name is the MAC address, the value is the IP address.</li> </ul> </li> </ul>
ip_appliance_returnpath_json	A Traffic Manager REST-compatible JSON representation of the "ip_appliance_returnpath" table property. Use this field with the "vtm_global_settings_appliance_returnpath_table" data source for dynamic table generation from input variables.  • Type: String  • Required: false  • Default value: <none></none>
java_classpath	CLASSPATH to use when starting the Java runner.  Type: String Required: false Default value: <none></none>

Property	Description
java_command	Java command to use when starting the Java runner, including any additional options.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "java -server"</li></ul>
java_enabled	Whether or not Java support should be enabled. If this is set to No, then your traffic manager will not start any Java processes. Java support is only required if you are using the TrafficScript java.run() function.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
java_lib	Java library directory for additional jar files. The Java runner will load classes from any .jar files stored in this directory, as well as the * jar files and classes stored in traffic manager's catalog.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
java_max_connections	Maximum number of simultaneous Java requests. If there are more than this many requests, then further requests will be queued until the earlier requests are completed. This setting is per-CPU, so if your traffic manager is running on a machine with 4 CPU cores, then each core can make this many requests at one time.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "256"</li></ul>
java_session_age	Default time to keep a Java session.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "86400"</li></ul>
kerberos_verbose	Whether or not a traffic manager should log all Kerberos related activity. This is very verbose, and should only be used for diagnostic purposes.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
l4accel_max_concurrent_conn ections	The maximum number of concurrent connections, in millions, that can be handled by each L4Accel child process. An appropriate amount of memory to store this many connections will be allocated when the traffic manager starts.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "1"</li></ul>

Property	Description
license_servers	A list of license servers for FLA licensing. A license server should be specified as a <ip host="">:<port> pair.</port></ip>
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
log_error_level	The minimum severity of events/alerts that should be logged to disk. INFO will log all events; a higher severity setting will log fewer events. More fine-grained control can be achieved using events and actions.
	<ul> <li>Type: Enum(UInt)</li> <li>Required: false</li> <li>Default value: "info"</li> <li>Permitted values:         "fatal": Only fatal errors are logged</li> </ul>
	"info": All events are logged to disk
	"serious": Only serious errors or worse
	"warn": Only warnings and errors are logged
log_export_auth_hec_token	The HTTP Event Collector token to use for HTTP authentication with a Splunk server.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
log_export_auth_http	The HTTP authentication method to use when exporting log entries.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "none"</li> <li>Permitted values: "basic": Basic (Username and Password)</li> </ul>
	"none": None
	"splunk": Splunk (HEC token)
log_export_auth_password	The password to use for HTTP basic authentication.
	<ul><li>Type: Password</li><li>Required: false</li><li>Default value: <none></none></li></ul>
log_export_auth_username	The username to use for HTTP basic authentication.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
log_export_enabled	Monitor log files and export entries to the configured endpoint.  Type: Boolean Required: false Default value: false

Property	Description
log_export_endpoint	The URL to which log entries should be sent. Entries are sent using HTTP(S) POST requests.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
log_export_request_timeout	The number of seconds after which HTTP requests sent to the configured endpoint will be considered to have failed if no response is received. A value of 0 means that HTTP requests will not time out.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "30"</li></ul>
log_export_tls_verify	Whether the server certificate should be verified when connecting to the endpoint. If enabled, server certificates that do not match the server name, are self-signed, have expired, have been revoked, or that are signed by an unknown CA will be rejected.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
log_flush_time	How long to wait before flushing the request log files for each virtual server.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "5"</li></ul>
log_log_file	The file to log event messages to.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "%zeushome%/zxtm/log/errors"</li></ul>
log_rate	The maximum number of connection errors logged per second when connection error reporting is enabled.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "50"</li></ul>
log_reopen	How long to wait before re-opening request log files, this ensures that log files will be recreated in the case of log rotation.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "30"</li></ul>
log_time	The minimum time between log messages for log intensive features such as SLM.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "60"</li></ul>

Property	Description
max_fds	The maximum number of file descriptors that your traffic manager will allocate.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "1048576"</li></ul>
monitor_memory_size	The maximum number of each of nodes, pools or locations that can be monitored. The memory used to store information about nodes, pools and locations is allocated at start-up, so the traffic manager must be restarted after changing this setting.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "4096"</li></ul>
ospfv2_area	The OSPF area in which the traffic manager will operate. May be entered in decimal or IPv4 address format.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "0.0.0.1"</li></ul>
ospfv2_area_type	The type of OSPF area in which the traffic manager will operate. This must be the same for all routers in the area, as required by OSPF.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "normal"</li> <li>Permitted values:    "normal": Normal area</li> </ul>
	"nssa": Not So Stubby Area (RFC3101) "stub": Stub area
ospfv2_authentication_key_id_ a	OSPFv2 authentication key ID. If set to 0, which is the default value, the key is disabled.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ospfv2_authentication_key_id_ b	OSPFv2 authentication key ID. If set to 0, which is the default value, the key is disabled.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ospfv2_authentication_shared _secret_a	OSPFv2 authentication shared secret (MD5). If set to blank, which is the default value, the key is disabled.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
ospfv2_authentication_shared _secret_b	OSPFv2 authentication shared secret (MD5). If set to blank, which is the default value, the key is disabled.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ospfv2_enabled	Whether OSPFv2 Route Health Injection is enabled
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ospfv2_hello_interval	The interval at which OSPF "hello" packets are sent to the network.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "10"</li></ul>
ospfv2_router_dead_interval	The number of seconds before declaring a silent router down.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "40"</li></ul>
protection_conncount_size	The amount of shared memory reserved for an inter-process table of combined connection counts, used by all Service Protection classes that have per_process_connection_count set to No. The amount is specified as an absolute size, eg 20MB.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "20MB"</li></ul>
rate_class_limit	The maximum number of Rate classes that can be created. Approximately 100 bytes will be pre-allocated per Rate class.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "25000"</li></ul>
recent_connections_max_per_ process	How many recently closed connections each traffic manager process should save. These saved connections will be shown alongside currently active connections when viewing the Connections page. You should set this value to 0 in a benchmarking or performance-critical environment.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "500"</li></ul>
recent_connections_retain_ti me	The amount of time for which snapshots will be retained on the Connections page.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "60"</li></ul>

Property	Description
recent_connections_snapshot _size	The maximum number of connections each traffic manager process should show when viewing a snapshot on the Connections page. This value includes both currently active connections and saved connections. If set to 0 all active and saved connection will be displayed on the Connections page.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "500"</li></ul>
remote_licensing_owner	The Owner of a Services Director instance, used for self-registration.  Type: String Required: false Default value: <none></none>
remote_licensing_owner_secr et	The secret associated with the Owner.  Type: String Required: false Default value: <none></none>
remote_licensing_policy_id	The auto-accept Policy ID that this instance should attempt to use.  Type: String Required: false Default value: <none></none>
remote_licensing_registration_ server	A Services Director address for self-registration. A registration server should be specified as a <ip host="">:<port> pair.  Type: String Required: false Default value: <none></none></port></ip>
remote_licensing_server_certificate	The certificate of a Services Director instance, used for self-registration.  Type: String Required: false Default value: <none></none>
rest_api_auth_timeout	The length of time after a successful request that the authentication of a given username and password will be cached for an IP address. A setting of 0 disables the cache forcing every REST request to be authenticated which will adversely affect performance.  Type: UInt Required: false Default value: "120"
rest_api_enabled	Whether or not the REST service is enabled.  • Type: Boolean  • Required: false  • Default value: false
rest_api_http_max_header_len gth	The maximum allowed length in bytes of a HTTP request's headers.  • Type: UInt  • Required: false  • Default value: "4096"

Property	Description
rest_api_replicate_absolute	Configuration changes will be replicated across the cluster after this period of time, regardless of whether additional API requests are being made.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "20"</li></ul>
rest_api_replicate_lull	Configuration changes made via the REST API will be propagated across the cluster when no further API requests have been made for this period of time.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "5"</li></ul>
rest_api_replicate_timeout	The period of time after which configuration replication across the cluster will be cancelled if it has not completed.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>
security_login_banner	Banner text displayed on the Admin Server login page and before logging in to appliance SSH servers.
	<ul><li>Type: FreeformString</li><li>Required: false</li><li>Default value: <none></none></li></ul>
security_login_banner_accept	Whether or not users must explicitly agree to the displayed login_banner text before logging in to the Admin Server.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
security_login_delay	The number of seconds before another login attempt can be made after a failed attempt.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "4"</li></ul>
security_max_login_attempts	The number of sequential failed login attempts that will cause a user account to be suspended. Setting this to 0 disables this feature. To apply this to users who have never successfully logged in, track_unknown_users must also be enabled.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
security_max_login_external	Whether or not usernames blocked due to the max_login_attempts limit should also be blocked from authentication against external services (such as LDAP and RADIUS).
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

Property	Description
security_max_login_suspensio n_time	The number of minutes to suspend users who have exceeded the max_login_attempts limit.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "15"</li></ul>
security_password_allow_cons ecutive_chars	Whether or not to allow the same character to appear consecutively in passwords.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
security_password_changes_p er_day	The maximum number of times a password can be changed in a 24-hour period. Set to 0 to disable this restriction.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
security_password_min_alpha _chars	Minimum number of alphabetic characters a password must contain. Set to 0 to disable this restriction.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
security_password_min_length	Minimum number of characters a password must contain. Set to 0 to disable this restriction.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
security_password_min_nume ric_chars	Minimum number of numeric characters a password must contain. Set to 0 to disable this restriction.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
security_password_min_specia l_chars	Minimum number of special (non-alphanumeric) characters a password must contain. Set to 0 to disable this restriction.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
security_password_min_upper case_chars	Minimum number of uppercase characters a password must contain. Set to 0 to disable this restriction.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
security_password_reuse_afte	The number of times a password must have been changed before it can be reused. Set to 0 to disable this restriction.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
security_post_login_banner	Banner text to be displayed on the appliance console after login.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
security_track_unknown_users	Whether to remember past login attempts from usernames that are not known to exist (should be set to false for an Admin Server accessible from the public Internet). This does not affect the audit log.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
security_ui_page_banner	Banner text to be displayed on all Admin Server pages.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
session_asp_cache_size	The maximum number of entries in the ASP session cache. This is used for storing session mappings for ASP session persistence. Approximately 100 bytes will be pre-allocated per entry.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "32768"</li></ul>
session_ip_cache_size	The maximum number of entries in the IP session cache. This is used to provide session persistence based on the source IP address. Approximately 100 bytes will be pre-allocated per entry.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "32768"</li></ul>
session_j2ee_cache_size	The maximum number of entries in the J2EE session cache. This is used for storing session mappings for J2EE session persistence. Approximately 100 bytes will be pre-allocated per entry.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "32768"</li></ul>
session_ssl_cache_size	The maximum number of entries in the SSL session persistence cache. This is used to provide session persistence based on the SSL session ID. Approximately 200 bytes will be pre-allocated per entry.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "32768"</li></ul>

Property	Description
session_universal_cache_size	The maximum number of entries in the global universal session cache. This is used for storing session mappings for universal session persistence. Approximately 100 bytes will be pre-allocated per entry.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "32768"</li></ul>
shared_pool_size	The size of the shared memory pool used for shared storage across worker processes (e.g. bandwidth shared data). This is specified as either a percentage of system RAM, 5% for example, or an absolute size such as 10MB.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "10MB"</li></ul>
slm_class_limit	The maximum number of SLM classes that can be created. Approximately 100 bytes will be pre-allocated per SLM class.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "1024"</li></ul>
snmp_user_counters	The number of user defined SNMP counters. Approximately 100 bytes will be pre-allocated at start-up per user defined SNMP counter.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>
so_rbuff_size	The size of the operating system's read buffer. A value of 0 (zero) means to use the OS default; in normal circumstances this is what should be used.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
so_wbuff_size	The size of the operating system's write buffer. A value of 0 (zero) means to use the OS default; in normal circumstances this is what should be used.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
soap_idle_minutes	The number of minutes that the SOAP server should remain idle before exiting. The SOAP server has a short startup delay the first time a SOAP request is made, subsequent SOAP requests don't have this delay.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>

Property	Description
socket_optimizations	Whether or not the traffic manager should use potential network socket optimisations. If set to auto, a decision will be made based on the host platform.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "auto"</li> <li>Permitted values: "auto": Decide based on local platform</li> </ul>
	"no": Disable socket optimizations
	"yes": Enable socket optimizations
source_nat_ip_limit	The maximum number of Source NAT IP addresses that can be used across all Traffic IP Groups.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "16"</li></ul>
source_nat_ip_local_port_rang e_high	The upper boundary of the port range reserved for use by the kernel. Ports above this range will be used by the traffic manager for establishing outgoing connections.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10240"</li></ul>
source_nat_shared_pool_size	The size of the Source NAT shared memory pool used for shared storage across child processes. This value is specified as an absolute size such as 10MB.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>
ssl_cache_expiry	How long the SSL session IDs for SSL decryption should be stored for.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "1800"</li></ul>
ssl_cache_per_virtualserver	Whether an SSL session created by a given virtual server can only be resumed by a connection to the same virtual server.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_cache_size	How many entries the SSL session ID cache should hold. This cache is used to cache SSL sessions to help speed up SSL handshakes when performing SSL decryption. To turn off SSL session resumption, set this key to the value 0. Each entry will allocate approximately 1.5kB of metadata.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "6151"</li></ul>

Property	Description
ssl_crl_mem_size	How much shared memory to allocate for loading Certificate Revocation Lists. This should be at least 3 times the total size of all CRLs on disk. This is specified as either a percentage of system RAM, 1% for example, or an absolute size such as 10MB.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "5MB"</li></ul>
ssl_elliptic_curves	The SSL elliptic curve preference list for SSL connections using TLS version 1.0 or higher, unless overridden by virtual server or pool settings. The named curves P256, P384 and P521 may be configured.
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_hardware_accel	Whether or not the SSL hardware is an "accelerator" (faster than software). By default the traffic manager will only use the SSL hardware if a key requires it (i.e. the key is stored on secure hardware and the traffic manager only has a placeholder/identifier key). With this option enabled, your traffic manager will instead try to use hardware for all SSL decrypts.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_hardware_azure_client_id	The client identifier used when accessing the Microsoft Azure Key Vault.  Type: String Required: false Default value: <none></none>
ssl_hardware_azure_client_sec ret	The client secret used when accessing the Microsoft Azure Key Vault.  Type: Password Required: false Default value: <none></none>
ssl_hardware_azure_vault_url	The URL for the REST API of the Microsoft Azure Key Vault.  • Type: String  • Required: false  • Default value: <none></none>
ssl_hardware_azure_verify_res t_api_cert	Whether or not the Azure Key Vault REST API certificate should be verified.  Type: Boolean Required: false Default value: false
ssl_hardware_driver_pkcs11_d ebug	Print verbose information about the PKCS11 hardware security module to the event log.  Type: Boolean Required: false Default value: false

Property	Description
ssl_hardware_driver_pkcs11_li b	The location of the PKCS#11 library for your SSL hardware if it is not in a standard location. The traffic manager will search the standard locations by default.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_hardware_driver_pkcs11_sl ot_desc	The label of the SSL Hardware slot to use. Only required if you have multiple HW accelerator slots.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_hardware_driver_pkcs11_sl	The type of SSL hardware slot to use.
ot_type	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "operator"</li> <li>Permitted values:    "module": Module Protected</li> </ul>
	"operator": Operator Card Set
	"softcard": Soft Card
ssl_hardware_driver_pkcs11_u	The User PIN for the PKCS token (PKCS#11 devices only).
ser_pin	<ul><li>Type: Password</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_hardware_failure_count	The number of consecutive failures from the SSL hardware that will be tolerated before the traffic manager assumes its session with the device is invalid and tries to log in again. This is necessary when the device reboots following a power failure.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "5"</li></ul>
ssl_hardware_library	The type of SSL hardware to use. The drivers for the SSL hardware should be installed and accessible to the traffic manager software.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "none"</li> <li>Permitted values: "azure": Microsoft Azure Key Vault</li> </ul>
	"none": None "pkcs11": PKCS#11 (e.g. nCipher NetHSM)
ssl_honor_fallback_scsv	Whether or not ssl-decrypting Virtual Servers honor the Fallback SCSV to protect connections against downgrade attacks.
	<ul> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>

Property	Description
ssl_insert_extra_fragment	Whether or not SSL3 and TLS1 use one-byte fragments as a BEAST countermeasure.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_max_handshake_message_ size	The maximum size (in bytes) of SSL handshake messages that SSL connections will accept. To accept any size of handshake message the key should be set to the value 0.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "10240"</li></ul>
ssl_ocsp_cache_size	The maximum number of cached client certificate OCSP results stored. This cache is used to speed up OCSP checks against client certificates by caching results. Approximately 1040 bytes are pre-allocated per entry.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "2048"</li></ul>
ssl_ocsp_stapling_default_refr esh_interval	How long to wait before refreshing requests on behalf of the store of certificate status responses used by OCSP stapling, if we don't have an up-to-date OCSP response.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "60"</li></ul>
ssl_ocsp_stapling_maximum_r efresh_interval	Maximum time to wait before refreshing requests on behalf of the store of certificate status responses used by OCSP stapling. (0 means no maximum.)
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "864000"</li></ul>
ssl_ocsp_stapling_mem_size	How much shared memory to allocate for the store of certificate status responses for OCSP stapling. This should be at least 2kB times the number of certificates configured to use OCSP stapling. This is specified as either a percentage of system RAM, 1% for example, or an absolute size such as 10MB.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "1MB"</li></ul>
ssl_ocsp_stapling_time_toleran ce	How many seconds to allow the current time to be outside the validity time of an OCSP response before considering it invalid.  • Type: UInt  • Required: false  • Default value: "30"

Property	Description
ssl_ocsp_stapling_verify_response	Whether the OCSP response signature should be verified before the OCSP response is cached.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_prevent_timing_side_chan nels	Take performance degrading steps to prevent exposing timing side- channels with SSL3 and TLS.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_signature_algorithms	The SSL signature algorithms preference list for SSL connections unless overridden by virtual server or pool settings. For information on supported algorithms see the online help.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_ssl3_allow_rehandshake	Whether or not SSL3/TLS re-handshakes should be supported. Enabling support for re-handshakes can expose services to Man-in-the-Middle attacks. It is recommended that only "safe" handshakes be permitted, or none at all.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "safe"</li> <li>Permitted values:    "always": Always allow</li> </ul>
	"never": Never allow "rfc5746": Only if client uses RFC 5746 (Secure Renegotiation Extension)
	"safe": Allow safe re-handshakes
ssl_ssl3_ciphers	The SSL ciphers to use. For information on supported ciphers see the online help.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_ssl3_diffie_hellman_key_len gth	The length in bits of the Diffie-Hellman key for ciphers that use Diffie-Hellman key agreement.
	<ul> <li>Type: Enum(UInt)</li> <li>Required: false</li> <li>Default value: "dh_2048"</li> <li>Permitted values: "dh_1024": 1024</li> </ul>
	"dh_2048": 2048 "dh_3072": 3072 "dh_4096": 4096

Property	Description
ssl_ssl3_min_rehandshake_int erval	If SSL3/TLS re-handshakes are supported, this defines the minimum time interval (in milliseconds) between handshakes on a single SSL3/TLS connection that is permitted. To disable the minimum interval for handshakes the key should be set to the value 0.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "1000"</li></ul>
ssl_support_ssl2	No longer supported. Formerly controlled whether SSL2 could be used by default.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_support_ssl3	Whether or not SSL3 support is enabled.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_support_tls1	Whether or not TLS1.0 support is enabled.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_support_tls1_1	Whether or not TLS1.1 support is enabled.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_support_tls1_2	Whether or not TLS1.2 support is enabled.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
tip_class_limit	The maximum number of Traffic IP Groups that can be created.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "10000"</li></ul>
trafficscript_array_elements	The amount of storage that will be allocated to array elements in TrafficScript. If more elements are required then the necessary memory will be allocated during the execution of the rule.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "100000"</li></ul>
trafficscript_data_local_size	The maximum amount of memory available to store TrafficScript data.local.set() information. This can be specified as a percentage of system RAM, 5% for example; or an absolute size such as 200MB.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "5%"</li></ul>

Property	Description
trafficscript_data_size	The maximum amount of memory available to store TrafficScript data.set() information. This can be specified as a percentage of system RAM, 5% for example; or an absolute size such as 200MB.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "5%"</li></ul>
trafficscript_execution_time_w arning	Raise an event if a TrafficScript rule runs for more than this number of milliseconds in a single invocation. If you get such events repeatedly, you may want to consider re-working some of your TrafficScript rules. A value of 0 means no warnings will be issued.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "500"</li></ul>
trafficscript_max_instr	The maximum number of instructions a TrafficScript rule will run. A rule will be aborted if it runs more than this number of instructions without yielding, preventing infinite loops.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "100000"</li></ul>
trafficscript_memory_warning	Raise an event if a TrafficScript rule requires more than this amount of buffered network data. If you get such events repeatedly, you may want to consider re-working some of your TrafficScript rules to use less memory or to stream the data that they process rather than storing it all in memory. This setting also limits the amount of data that can be returned by request. GetLine().
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "1048576"</li></ul>
trafficscript_regex_cache_size	The maximum number of regular expressions to cache in TrafficScript. Regular expressions will be compiled in order to speed up their use in the future.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "57"</li></ul>
trafficscript_regex_match_limit	The maximum number of ways TrafficScript will attempt to match a regular expression at each position in the subject string, before it aborts the rule and reports a TrafficScript error.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10000000"</li></ul>
trafficscript_regex_match_war n_percentage	The percentage of regex_match_limit at which TrafficScript reports a performance warning.  Type: Ulnt Required: false Default value: "5"

Property	Description
trafficscript_variable_pool_use	Allow the pool.use and pool.select TrafficScript functions to accept variables instead of requiring literal strings. Enabling this feature has the following effects1. Your traffic manager may no longer be able to know whether a pool is in use.2. Errors for pools that aren't in use will not be hidden.3. Some settings displayed for a Pool may not be appropriate for the type of traffic being managed.4. Pool usage information on the pool edit pages and config summary may not be accurate.5. Monitors will run for all pools (with this option disabled monitors will only run for Pools that are used).
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
transaction_export_enabled	Export metadata about transactions processed by the traffic manager to an external location.  Type: Boolean Required: false Default value: false
transaction_export_endpoint	The endpoint to which transaction metadata should be exported. The endpoint is specified as a hostname or IP address with a port.  Type: String Required: false Default value: <none></none>
transaction_export_tls	Whether the connection to the specified endpoint should be encrypted.  Type: Boolean Required: false Default value: false
transaction_export_tls_verify	Whether the server certificate presented by the endpoint should be verified, preventing a connection from being established if the certificate does not match the server name, is self-signed, is expired, is revoked, or has an unknown CA.  Type: Boolean Required: false Default value: false
web_cache_avg_path_length	The estimated average length of the path (including query string) for resources being cached. An amount of memory equal to this figure multiplied by max_file_num will be allocated for storing the paths for cache entries. This setting can be increased if your web site makes extensive use of long URLs.  Type: Ulnt Required: false Default value: "512"

Property	Description
web_cache_disk	Whether or not to use a disk-backed (typically SSD) cache. If set to Yes cached web pages will be stored in a file on disk. This enables the traffic manager to use a cache that is larger than available RAM. The size setting should also be adjusted to select a suitable maximum size based on your disk space. Note that the disk caching is optimized for use with SSD storage.  Type: Boolean Required: false Default value: false
web_cache_disk_dir	If disk caching is enabled, this sets the directory where the disk cache file will be stored. The traffic manager will create a file called webcache.data in this location. Note that the disk caching is optimized for use with SSD storage.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "%zeushome%/zxtm/internal"</li></ul>
web_cache_max_file_num	Maximum number of entries in the cache. Approximately 0.9 KB will be pre-allocated per entry for metadata, this is in addition to the memory reserved for the content cache and for storing the paths of the cached resources.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "10000"</li></ul>
web_cache_max_file_size	Largest size of a cacheable object in the cache. This is specified as either a percentage of the total cache size, 2% for example, or an absolute size such as 20MB.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "2%"</li></ul>
web_cache_max_path_length	The maximum length of the path (including query string) for the resource being cached. If the path exceeds this length then it will not be added to the cache.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "2048"</li></ul>
web_cache_normalize_query	<ul> <li>Enable normalization (lexical ordering of the parameter-assignments) of the query string.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>

Property	Description
web_cache_size	The maximum size of the HTTP web page cache. This is specified as either a percentage of system RAM, 20% for example, or an absolute size such as 200MB.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "20%"</li></ul>
web_cache_verbose	Add an X-Cache-Info header to every HTTP response, showing whether the request and/or the response was cacheable.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

#### vtm\_kerberos\_krb5conf

URI Endpoint: /api/tm/4.0/config/active/kerberos/krb5confs

A Kerberos krb5.conf file that provides the raw configuration for a Kerberos principal.

```
# Example usage of vtm_kerberos_krb5conf resource...
resource "vtm_kerberos_krb5conf" "my_kerberos_krb5conf" {
    content = ""
    name = "MyKerberosKrb5Conf"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
content	Object content
	<ul><li>Type: string</li><li>Required: true</li></ul>

## vtm\_kerberos\_keytab

URI Endpoint: /api/tm/4.0/config/active/kerberos/keytabs

A Kerberos keytab file contains credentials to authenticate as (a number of) Kerberos principals.

```
# Example usage of vtm_kerberos_keytab resource...
resource "vtm_kerberos_keytab" "my_kerberos_keytab" {
    content = ""
    name = "MyKerberosKeytab"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
content	Object content
	<ul><li>Type: string</li><li>Required: true</li></ul>

# vtm\_kerberos\_principal

URI Endpoint: /api/tm/4.0/config/active/kerberos/principals

A Kerberos principal can be used by the traffic manager to participate in a Kerberos realm.

```
# Example usage of vtm_kerberos_principal resource...
resource "vtm_kerberos_principal" "my_kerberos_principal" {
    keytab =
    name = "MyKerberosPrincipal"
    service =
}
```

Property	Description
name	Name of the object  Type: string Required: true
kdcs	A list of <hostname ip="">:<port> pairs for Kerberos key distribution center (KDC) services to be explicitly used for the realm of the principal. If no KDCs are explicitly configured, DNS will be used to discover the KDC(s) to use.</port></hostname>
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
keytab	The name of the Kerberos keytab file containing suitable credentials to authenticate as the specified Kerberos principal.  Type: String
	<ul><li>Required: true</li><li>Default value: <none></none></li></ul>
krb5conf	<ul> <li>The name of an optional Kerberos configuration file (krb5.conf).</li> <li>Type: String</li> <li>Required: false</li> <li>Default value: <none></none></li> </ul>

Property	Description
realm	The Kerberos realm where the principal belongs.  • Type: String
	<ul><li>Required: false</li><li>Default value: <none></none></li></ul>
service	The service name part of the Kerberos principal name the traffic manager should use to authenticate itself.
	<ul><li>Type: String</li><li>Required: true</li><li>Default value: <none></none></li></ul>

### vtm\_license\_key

URI Endpoint: /api/tm/4.0/config/active/license\_keys

A license key is a encoded text file that controls what functionality is available from each traffic manager in the cluster. Every production traffic manager must have a valid licence key in order to function; a traffic manager without a license will operate in developer mode, allowing developers to trial a wide range of functionality, but placing restrictions on bandwidth.

```
# Example usage of vtm_license_key resource...
resource "vtm_license_key" "my_license_key" {
    content = ""
    name = "MyLicenseKey"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
content	Object content
	<ul><li>Type: string</li><li>Required: true</li></ul>

#### vtm\_location

URI Endpoint: /api/tm/4.0/config/active/locations

These are geographic locations as used by Global Load Balancing services. Such a location may not necessarily contain a traffic manager; instead it could refer to the location of a remote datacenter.

```
# Example usage of vtm_location resource...
resource "vtm_location" "my_location" {
   id =
    name = "MyLocation"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
identifier	The identifier of this location.
	<ul><li>Type: UInt</li><li>Required: true</li><li>Default value: <none></none></li></ul>
latitude	The latitude of this location.
	<ul><li>Type: Float</li><li>Required: false</li><li>Default value: "0.0"</li></ul>
longitude	The longitude of this location.
	<ul><li>Type: Float</li><li>Required: false</li><li>Default value: "0.0"</li></ul>
note	A note, used to describe this location.
	<ul><li>Type: FreeformString</li><li>Required: false</li><li>Default value: <none></none></li></ul>
type	Does this location contain traffic managers and configuration or is it a recipient of GLB requests?
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "config"</li> <li>Permitted values: "config": Configuration</li> <li>"glb": GLB</li> </ul>

## vtm\_log\_export

URI Endpoint: /api/tm/4.0/config/active/log\_export

Definitions of log files which should be exported to the analytics engine

```
# Example usage of vtm_log_export resource...
resource "vtm_log_export" "my_log_export" {
    name = "MyLogExport"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
appliance_only	Whether entries from the specified log files should be exported only from appliances.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
enabled	Export entries from the log files included in this category.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
files	The set of files to export as part of this category, specified as a list of glob patterns.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
history	How much historic log activity should be exported.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "none"</li> <li>Permitted values:     "all": Export all historic entries</li> </ul>
	"none": Do not export any historic entries
	"recent": Export recent historic entries, according to the 'history_period' setting
history_period	The number of days of historic log entries that should be exported.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>
metadata	This is table 'metadata'
	<ul> <li>Type: Table</li> <li>Required: false</li> <li>Primary key:         <ul> <li>name (String): The name of a metadata item which should be sent to the analytics engine along with entries from these log files. (Required)</li> </ul> </li> <li>Sub keys:         <ul> <li>value (String): Additional metadata to include with the log entries when exporting them to the configured endpoint. Metadata can be used by the system that is receiving the exported data to categorise and parse the log entries.</li> </ul> </li> </ul>

Property	Description
metadata_json	A Traffic Manager REST-compatible JSON representation of the "metadata" table property. Use this field with the "vtm_log_export_metadata_table" data source for dynamic table generation from input variables.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
note	A description of this category of log files.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>

### vtm\_monitor

URI Endpoint: /api/tm/4.0/config/active/monitors

Monitors check important remote services are running, by periodically sending them traffic and checking the response is correct. They are used by virtual servers to detect the failure of backend nodes.

```
# Example usage of vtm_monitor resource...
resource "vtm_monitor" "my_monitor" {
    name = "MyMonitor"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
back_off	Should the monitor slowly increase the delay after it has failed?
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
delay	The minimum time between calls to a monitor.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "3"</li></ul>
failures	The number of times in a row that a node must fail execution of the monitor before it is classed as unavailable.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "3"</li></ul>

Property	Description
health_only	Should this monitor only report health (ignore load)?
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
http_authentication	The HTTP basic-auth <user>:<password> to use for the test HTTP request.</password></user>
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
http_body_regex	A regular expression that the HTTP response body must match. If the response body content doesn't matter then set this to .* (match anything).
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
http_host_header	The host header to use in the test HTTP request.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
http_path	The path to use in the test HTTP request. This must be a string beginning with a / (forward slash).
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "/"</li></ul>
http_status_regex	A regular expression that the HTTP status code must match. If the status code doesn't matter then set this to .* (match anything).
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "^[234][0-9][0-9]\$"</li></ul>
machine	The machine to monitor, where relevant this should be in the form <hostname>:<port>, for "ping" monitors the :<port> part must not be specified.</port></port></hostname>
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
note	A description of the montitor.
	<ul><li>Type: FreeformString</li><li>Required: false</li><li>Default value: <none></none></li></ul>
rtsp_body_regex	The regular expression that the RTSP response body must match.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
rtsp_path	The path to use in the RTSP request (some servers will return 500 Internal Server Error unless this is a valid media file).
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "/"</li></ul>
rtsp_status_regex	The regular expression that the RTSP response status code must match.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "^[234][0-9][0-9]\$"</li></ul>
scope	A monitor can either monitor each node in the pool separately and disable an individual node if it fails, or it can monitor a specific machine and disable the entire pool if that machine fails. GLB location monitors must monitor a specific machine.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "pernode"</li> <li>Permitted values:     "pernode": Node: Monitor each node in the pool separately</li> </ul>
	"poolwide": Pool/GLB: Monitor a specified machine
script_arguments	<ul> <li>A table containing arguments and argument values to be passed to the monitor program.</li> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>name (String): The name of the argument to be passed to the monitor program. (Required)</li> </ul> </li> <li>Sub keys: <ul> <li>value (String): The value of the argument to be passed to the monitor program.</li> <li>description (String): A description for the argument provided to the program.</li> </ul> </li> </ul>
script_arguments_json	A Traffic Manager REST-compatible JSON representation of the "script_arguments" table property. Use this field with the "vtm_monitor_arguments_table" data source for dynamic table generation from input variables.  • Type: String • Required: false • Default value: <none></none>
script_program	The program to run. This must be an executable file, either within the monitor scripts directory or specified as an absolute path to some other location on the filesystem.  Type: String Required: false Default value: <none></none>

Property	Description
sip_body_regex	The regular expression that the SIP response body must match.  • Type: String  • Required: false  • Default value: <none></none>
sip_status_regex	The regular expression that the SIP response status code must match.  • Type: String  • Required: false  • Default value: "^[234][0-9][0-9]\$"
sip_transport	<ul> <li>Which transport protocol the SIP monitor will use to query the server.</li> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "udp"</li> <li>Permitted values:     "tcp": TCP</li> <li>"udp": UDP</li> </ul>
tcp_close_string	An optional string to write to the server before closing the connection.  Type: String Required: false Default value: <none></none>
tcp_max_response_len	The maximum amount of data to read back from a server, use 0 for unlimited. Applies to TCP and HTTP monitors.  Type: UInt Required: false Default value: "2048"
tcp_response_regex	A regular expression to match against the response from the server. Applies to TCP monitors only.  Type: String Required: false Default value: ".+"
tcp_write_string	The string to write down the TCP connection.  Type: String Required: false Default value: <none></none>
timeout	The maximum runtime for an individual instance of the monitor.  Type: UInt Required: false Default value: "3"

Property	Description
type	The internal monitor implementation of this monitor.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "ping"</li> <li>Permitted values: "connect": TCP Connect monitor</li> </ul>
	"http": HTTP monitor
	"ping": Ping monitor
	"program": External program monitor
	"rtsp": RTSP monitor
	"sip": SIP monitor
	"tcp_transaction": TCP transaction monitor
udp_accept_all	If this monitor uses UDP, should it accept responses from any IP and port?
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
use_ssl	Whether or not the monitor should connect using SSL.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
verbose	Whether or not the monitor should emit verbose logging. This is useful for diagnosing problems.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

#### vtm\_monitor\_script

URI Endpoint: /api/tm/4.0/config/active/monitor\_scripts

An executable program that can be used to by external program monitors to report the health of backend services.

```
# Example usage of vtm_monitor_script resource...
resource "vtm_monitor_script" "my_monitor_script" {
    content = ""
    name = "MyMonitorScript"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
content	Object content
	<ul><li>Type: string</li><li>Required: true</li></ul>

### vtm\_appliance\_nat

URI Endpoint: /api/tm/4.0/config/active/appliance/nat

The NAT configuration file stores rules controlling NAT on an appliance.

```
# Example usage of vtm_appliance_nat resource...
resource "vtm_appliance_nat" "my_appliance_nat" {
.
```

Property	Description
many_to_one_all_ports	<ul> <li>This is table 'many_to_one_all_ports'</li> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>rule_number (String): A unique rule identifier (Required)</li> </ul> </li> <li>Sub keys: <ul> <li>pool (String): Pool of a "many to one overload" type NAT rule.</li> <li>tip (String): TIP Group of a "many to one overload" type NAT rule.</li> </ul> </li> </ul>
many_to_one_all_ports_json	A Traffic Manager REST-compatible JSON representation of the "many_to_one_all_ports" table property. Use this field with the "vtm_appliance_nat_many_to_one_all_ports_table" data source for dynamic table generation from input variables.  • Type: String • Required: false • Default value: <none></none>

Property	Description
many_to_one_port_locked	<ul> <li>This is table 'many_to_one_port_locked'</li> <li>Type: Table</li> <li>Required: false</li> <li>Primary key:  - rule_number (String): A unique rule identifier (Required)</li> <li>Sub keys:  - pool (String): Pool of a "many to one port locked" type NAT rule.</li> <li>port (UInt): Port number of a "many to one port locked" type NAT rule.</li> <li>protocol (Enum(String)): Protocol of a "many to one port locked" type NAT rule.</li> <li>Permitted values:  "icmp": ICMP  "sctp": SCTP  "tcp": TCP  "udp": UDP  "udplite": UDPLITE</li> <li>tip (String): TIP Group of a "many to one port locked" type NAT</li> </ul>
many_to_one_port_locked_jso n	rule.  A Traffic Manager REST-compatible JSON representation of the "many_to_one_port_locked" table property. Use this field with the "vtm_appliance_nat_many_to_one_port_locked_table" data source for dynamic table generation from input variables.  • Type: String • Required: false • Default value: <none></none>
one_to_one	<ul> <li>This is table 'one_to_one'</li> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>rule_number (String): A unique rule identifier (Required)</li> </ul> </li> <li>Sub keys: <ul> <li>enable_inbound (Boolean): Enabling the inbound part of a "one to one" type NAT rule.</li> <li>ip (String): IP Address of a "one to one" type NAT rule.</li> <li>tip (String): TIP group of a "one to one" type NAT rule.</li> </ul> </li> </ul>
one_to_one_json	A Traffic Manager REST-compatible JSON representation of the "one_to_one" table property. Use this field with the "vtm_appliance_nat_one_to_one_table" data source for dynamic table generation from input variables.  • Type: String • Required: false • Default value: <none></none>

Property	Description
port_mapping	<ul> <li>This is table 'port_mapping'</li> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>rule_number (String): A unique rule identifier (Required)</li> </ul> </li> <li>Sub keys: <ul> <li>dport_first (UInt): First port of the dest. port range of a "port mapping" rule.</li> <li>dport_last (UInt): Last port of the dest. port range of a "port mapping" rule.</li> <li>virtual_server (String): Target Virtual Server of a "port mapping" rule.</li> </ul> </li> </ul>
port_mapping_json	A Traffic Manager REST-compatible JSON representation of the "port_mapping" table property. Use this field with the "vtm_appliance_nat_port_mapping_table" data source for dynamic table generation from input variables.  Type: String Required: false Default value: <none></none>

### vtm\_pool

URI Endpoint: /api/tm/4.0/config/active/pools

The conf/pools directory contains configuration files for backend node pools. The name of a file is the name of the pool it defines. Pools can be configured under the Services > Pools section of the Admin Server UI or by using functions under the Pool section of the SOAP API and CLI.

```
# Example usage of vtm_pool resource...
resource "vtm_pool" "my_pool" {
    name = "MyPool"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
auto_scaling_addnode_delayti me	The time in seconds from the creation of the node which the traffic manager should wait before adding the node to the autoscaled pool. Set this to allow applications on the newly created node time to intialize before being sent traffic.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
auto_scaling_cloud_credential s	The Cloud Credentials object containing authentication credentials to use in cloud API calls.
	<ul><li>Type: Reference(cloud-api)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
auto_scaling_cluster	The ESX host or ESX cluster name to put the new virtual machine instances on.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
auto_scaling_data_center	The name of the logical datacenter on the vCenter server. Virtual machines will be scaled up and down under the datacenter root folder.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
auto_scaling_data_store	The name of the datastore to be used by the newly created virtual machine.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
auto_scaling_enabled	Are the nodes of this pool subject to autoscaling? If yes, nodes will be automatically added and removed from the pool by the chosen autoscaling mechanism.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
auto_scaling_external	Whether or not autoscaling is being handled by an external system. Set this value to Yes if all aspects of autoscaling are handled by an external system, such as RightScale. If set to No, the traffic manager will determine when to scale the pool and will communicate with the cloud provider to create and destroy nodes as necessary.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
auto_scaling_hysteresis	The time period in seconds for which a change condition must persist before the change is actually instigated.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "20"</li></ul>
auto_scaling_imageid	The identifier for the image of the instances to create.  Type: String Required: false Default value: <none></none>

Property	Description
auto_scaling_ips_to_use	Which type of IP addresses on the node to use. Choose private IPs if the traffic manager is in the same cloud as the nodes, otherwise choose public IPs.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "publicips"</li> <li>Permitted values:     "private_ips": Private IP addresses</li> </ul>
auto_scaling_last_node_idle_ti me	"publicips": Public IP addresses  The time in seconds for which the last node in an autoscaled pool must have been idle before it is destroyed. This is only relevant if min_nodes is 0.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "3600"</li></ul>
auto_scaling_max_nodes	The maximum number of nodes in this autoscaled pool.  Type: UInt Required: false Default value: "4"
auto_scaling_min_nodes	The minimum number of nodes in this autoscaled pool.  Type: UInt Required: false Default value: "1"
auto_scaling_name	The beginning of the name of nodes in the cloud that are part of this autoscaled pool.  Type: String Required: false Default value: <none></none>
auto_scaling_port	The port number to use for each node in this autoscaled pool.  Type: UInt Required: false Default value: "80"
auto_scaling_refractory	The time period in seconds after the instigation of a re-size during which no further changes will be made to the pool size.  Type: UInt Required: false Default value: "180"

Property	Description
auto_scaling_response_time	The expected response time of the nodes in ms. This time is used as a reference when deciding whether a node's response time is conforming. All responses from all the nodes will be compared to this reference and the percentage of conforming responses is the base for decisions about scaling the pool up or down.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "1000"</li></ul>
auto_scaling_scale_down_level	The fraction, in percent, of conforming requests above which the pool size is decreased. If the percentage of conforming requests exceeds this value, the pool is scaled down.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "95"</li></ul>
auto_scaling_scale_up_level	The fraction, in percent, of conforming requests below which the pool size is increased. If the percentage of conforming requests drops below this value, the pool is scaled up.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "40"</li></ul>
auto_scaling_securitygroupids	List of security group IDs to associate to the new EC2 instance.  • Type: Set(String)  • Required: false  • Default value: <none></none>
auto_scaling_size_id	The identifier for the size of the instances to create.  • Type: String  • Required: false  • Default value: <none></none>
auto_scaling_subnetids	List of subnet IDs where the new EC2-VPC instance(s) will be launched. Instances will be evenly distributed among the subnets. If the list is empty, instances will be launched inside EC2-Classic.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
bandwidth_class	The Bandwidth Management Class this pool uses, if any.  • Type: Reference(config-bandwidth)  • Required: false  • Default value: <none></none>
connection_max_connect_tim e	How long the pool should wait for a connection to a node to be established before giving up and trying another node.  Type: UInt Required: false Default value: "4"

Property	Description
connection_max_connections _per_node	The maximum number of concurrent connections allowed to each back-end node in this pool per machine. A value of 0 means unlimited connections.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
connection_max_queue_size	The maximum number of connections that can be queued due to connections limits. A value of 0 means unlimited queue size.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
connection_max_reply_time	How long the pool should wait for a response from the node before either discarding the request or trying another node (retryable requests only).
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "30"</li></ul>
connection_queue_timeout	The maximum time to keep a connection queued in seconds.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "10"</li></ul>
dns_autoscale_enabled	When enabled, the Traffic Manager will periodically resolve the hostnames in the "hostnames" list using a DNS query, and use the results to automatically add, remove or update the IP addresses of the nodes in the pool.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
dns_autoscale_hostnames	A list of hostnames which will be used for DNS-derived autoscaling
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
dns_autoscale_port	The port number to use for each node when using DNS-derived autoscaling
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "80"</li></ul>
failure_pool	If all of the nodes in this pool have failed, then requests can be diverted to another pool.
	<ul><li>Type: Reference(config-pool)</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
ftp_support_rfc_2428	Whether or not the backend IPv4 nodes understand the EPRT and EPSV command from RFC 2428. It is always assumed that IPv6 nodes support these commands.  Type: Boolean Required: false Default value: false
http_keepalive	Whether or not the pool should maintain HTTP keepalive connections to the nodes.  Type: Boolean Required: false Default value: false
http_keepalive_non_idempote nt	Whether or not the pool should maintain HTTP keepalive connections to the nodes for non-idempotent requests.  Type: Boolean Required: false Default value: false
kerberos_protocol_transition_ principal	The Kerberos principal the traffic manager should use when performing Kerberos Protocol Transition.  Type: String Required: false Default value: <none></none>
kerberos_protocol_transition_t arget	The Kerberos principal name of the service this pool targets.  Type: String Required: false Default value: <none></none>
l4accel_snat	Whether connections to the back-end nodes should appear to originate from an IP address raised on the traffic manager, rather than the IP address from which they were received by the traffic manager.  Type: Boolean Required: false Default value: false

Property	Description
load_balancing_algorithm	The load balancing algorithm that this pool uses to distribute load across its nodes.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "round_robin"</li> <li>Permitted values:     "fastest_response_time": The Response Time algorithm monitors     the response times for recent requests to each node. It sends each     new request to the node that has recently been responding the     most quickly.</li> </ul>
	"least_connections": This algorithm sends each new request to the node with the fewest currently active connections.
	"perceptive": The Perceptive algorithm uses a combination of response time data and connection counts to predict which node is likely to have the fastest response time for each request.
	"random": This algorithm chooses a random node for each request.
	"round_robin": This algorithm distributes traffic by assigning each request to a new node in turn.
	"weighted_least_connections": This algorithm works in a similar way to the Least Connections algorithm, but assigns more requests to nodes with a greater 'weight'.
	"weighted_round_robin": Weighted Round Robin works in a similar way to Round Robin, but assigns more requests to nodes with a greater 'weight'.
load_balancing_priority_enabl	Enable priority lists.
ed	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
load_balancing_priority_nodes	Minimum number of highest-priority active nodes.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "1"</li></ul>
max_connection_attempts	The maximum number of nodes to which the traffic manager will attempt to send a request before returning an error to the client. Requests that are non-retryable will be attempted against only one node. Zero signifies no limit.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
max_idle_connections_pernod e	The maximum number of unused HTTP keepalive connections that should be maintained to an individual node. Zero signifies no limit.  Type: UInt Required: false Default value: "50"

Property	Description
max_timed_out_connection_at tempts	The maximum number of connection attempts the traffic manager will make where the server fails to respond within the time limit defined by the max_reply_time setting. Zero signifies no limit.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "2"</li></ul>
monitors	The monitors assigned to this pool, used to detect failures in the back end nodes.
	<ul><li>Type: Set(Reference(config-monitor))</li><li>Required: false</li><li>Default value: <none></none></li></ul>
node_close_on_death	Close all connections to a node once we detect that it has failed.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
node_close_with_rst	Whether or not connections to the back-end nodes should be closed with a RST packet, rather than a FIN packet. This avoids the TIME_WAIT state, which on rare occasions allows wandering duplicate packets to be safely ignored.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
node_connection_attempts	The number of times the software will attempt to connect to the same back-end node before marking it as failed. This is only used when passive_monitoring is enabled.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "3"</li></ul>
node_delete_behavior	Specify the deletion behavior for nodes in this pool.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "immediate"</li> <li>Permitted values:     "drain": Allow existing connections to the node to finish before deletion.</li> </ul>
	"immediate": All connections to the node are closed immediately.
node_drain_to_delete_timeout	The maximum time that a node will be allowed to remain in a draining state after it has been deleted. A value of 0 means no maximum time.  Type: UInt Required: false Default value: <none></none>

Property	Description
node_retry_fail_time	The amount of time, in seconds, that a traffic manager will wait before re-trying a node that has been marked as failed by passive monitoring.  Type: UInt Required: false Default value: "60"
nodes_table	A table of all nodes in this pool. A node should be specified as a <ip>:<port> pair, and has a state, weight and priority.  Type: Table Required: false Primary key: node (String): A node is a combination of an ip address and port (Required)  Sub keys: priority (UInt): The priority of the node, higher values signify higher priority. If a priority is not specified for a node it is assumed to be 1. state (Enum(String)): The state of the pool, which can either be Active, Draining or Disabled Permitted values: "active": The node is disabled. "draining": The node is draining. weight (Int): Weight for the node. The actual value in isolation does not matter: As long as it is a valid integer 1-100, the pernode weightings are calculated on the relative values between the nodes. source_ip (String): The source address the Traffic Manager uses to connect to this node.</port></ip>
nodes_table_json  note	A Traffic Manager REST-compatible JSON representation of the "nodes_table" table property. Use this field with the "vtm_pool_nodes_table_table" data source for dynamic table generation from input variables.  Type: String Required: false Default value: <none>  A description of the pool.</none>
	<ul> <li>Type: String</li> <li>Required: false</li> <li>Default value: <none></none></li> </ul>

Property	Description
passive_monitoring	Whether or not the software should check that 'real' requests (i.e. not those from monitors) to this pool appear to be working. This should normally be enabled, so that when a node is refusing connections, responding too slowly, or sending back invalid data, it can mark that node as failed, and stop sending requests to it. If this is disabled, you should ensure that suitable health monitors are configured to check your servers instead, otherwise failed requests will not be detected and subsequently retried.  • Type: Boolean • Required: false • Default value: false
persistence_class	The default Session Persistence class this pool uses, if any.
	<ul><li>Type: Reference(config-persistence)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
smtp_send_starttls	If we are encrypting traffic for an SMTP connection, should we upgrade to SSL using STARTTLS.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_client_auth	Whether or not a suitable certificate and private key from the SSL Client Certificates catalog be used if the back-end server requests client authentication.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_common_name_match	A list of names against which the 'common name' of the certificate is matched; these names are used in addition to the node's hostname or IP address as specified in the config file or added by the autoscaler process.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_elliptic_curves	The SSL elliptic curve preference list for SSL connections from this pool using TLS version 1.0 or higher. Leaving this empty will make the pool use the globally configured preference list. The named curves P256, P384 and P521 may be configured.
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_enable	Whether or not the pool should encrypt data before sending it to a back-end node.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

Property	Description
ssl_enhance	SSL protocol enhancements allow your traffic manager to prefix each new SSL connection with information about the client. This enables Brocade vTM virtual servers referenced by this pool to discover the original client's IP address. Only enable this if you are using nodes for this pool which are Brocade Virtual Traffic Managers, whose virtual servers have the ssl_trust_magic setting enabled.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_send_close_alerts	Whether or not to send an SSL/TLS "close alert" when initiating a socket disconnection.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_server_name	Whether or not the software should use the TLS 1.0 server_name extension, which may help the back-end node provide the correct certificate. Enabling this setting will force the use of at least TLS 1.0.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_signature_algorithms	The SSL signature algorithms preference list for SSL connections from this pool using TLS version 1.2 or higher. Leaving this empty will make the pool use the globally configured preference list, signature_algorithms in the ssl section of the global_settings resource. See there and in the online help for how to specify SSL signature algorithms.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_ssl_ciphers	The SSL/TLS ciphers to allow for connections to a back-end node. Leaving this empty will make the pool use the globally configured ciphers, see configuration key ssl!ssl3_ciphers in the Global Settings section of the System tab. See there for how to specify SSL/TLS ciphers.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_ssl_support_ssl2	No longer supported. Formerly controlled whether SSLv2 could be used for SSL connections to pool nodes.  Type: Enum(String) Required: false Default value: "use_default" Permitted values: "disabled": Disable SSLv2 "enabled": Enable SSLv2 (not recommended) "use_default": Use the global setting for SSLv2

Property	Description
ssl_ssl_support_ssl3	Whether or not SSLv3 is enabled for this pool. Choosing the global setting means the value of the configuration key ssl!support_ssl3 from the Global Settings section of the System tab will be enforced.  Type: Enum(String) Required: false Default value: "use_default" Permitted values:
	"disabled": Disable SSLv3 "enabled": Enable SSLv3
	"use_default": Use the global setting for SSLv3
ssl_ssl_support_tls1	Whether or not TLSv1.0 is enabled for this pool. Choosing the global setting means the value of the configuration key ssl!support_tls1 from the Global Settings section of the System tab will be enforced.  • Type: Enum(String)
	<ul> <li>Required: false</li> <li>Default value: "use_default"</li> <li>Permitted values:    "disabled": Disable TLSv1.0</li> </ul>
	"enabled": Enable TLSv1.0
	"use_default": Use the global setting for TLSv1.0
ssl_ssl_support_tls1_1	Whether or not TLSv1.1 is enabled for this pool. Choosing the global setting means the value of the configuration key ssl!support_tls1.1 from the Global Settings section of the System tab will be enforced.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "use_default"</li> <li>Permitted values:   "disabled": Disable TLSv1.1</li> </ul>
	"enabled": Enable TLSv1.1
	"use_default": Use the global setting for TLSv1.1
ssl_ssl_support_tls1_2	Whether or not TLSv1.2 is enabled for this pool. Choosing the global setting means the value of the configuration key ssl!support_tls1.2 from the Global Settings section of the System tab will be enforced.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "use_default"</li> <li>Permitted values:     "disabled": Disable TLSv1.2     "enabled": Enable TLSv1.2     "use_default": Use the global setting for TLSv1.2</li> </ul>

Property	Description
ssl_strict_verify	Whether or not strict certificate verification should be performed. This will turn on checks to disallow server certificates that don't match the server name or a name in the ssl_common_name_match list, are self-signed, expired, revoked, or have an unknown CA.  Type: Boolean Required: false Default value: false
tcp_nagle	Whether or not Nagle's algorithm should be used for TCP connections to the back-end nodes.  Type: Boolean Required: false Default value: false
transparent	Whether or not connections to the back-ends appear to originate from the source client IP address.  Type: Boolean Required: false Default value: false
udp_accept_from	<ul> <li>The IP addresses and ports from which responses to UDP requests should be accepted. If set to accept responses from a specific set of IP addresses, you will need to enter a CIDR Mask (such as 10.100.0.0/16).</li> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "dest_only"</li> <li>Permitted values: "all": Any IP address and any port.</li> <li>"dest_ip_only": Only the IP address to which the request was sent, but from any port.</li> <li>"dest_only": Only the IP address and port to which the request was sent.</li> <li>"ip_mask": Only a specific set of IP addresses, but from any port.</li> </ul>
udp_accept_from_mask	The CIDR mask that matches IPs we want to receive responses from.  • Type: String  • Required: false  • Default value: <none></none>
udp_response_timeout	The maximum length of time that a node is permitted to take after receiving a UDP request packet before sending a reply packet. Zero indicates that there is no maximum, preventing a node that does not send replies from being presumed to have failed.  Type: UInt Required: false Default value: <none></none>

## $vtm\_protection$

URI Endpoint: /api/tm/4.0/config/active/protection

A protection class specifies the level of protection against network attacks for a virtual server.

```
# Example usage of vtm_protection resource...
resource "vtm_protection" "my_protection" {
    name = "MyProtection"
}
```

Property	Description
name	Name of the object  Type: string Required: true
access_restriction_allowed	Always allow access to these IP addresses. This overrides the connection limits for these machines, but does not stop other restrictions such as HTTP validity checks.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
access_restriction_banned	Disallow access to these IP addresses.  Type: Set(String) Required: false Default value: <none></none>
connection_limiting_max_10_c onnections	Additional limit on maximum simultaneous connections from the top 10 busiest connecting IP addresses combined. The value should be between 1 and 10 times the max_1_connections limit. (This limit is disabled if per_process_connection_count is No, or max_1_connections is 0, or min_connections is 0.)
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "200"</li></ul>
connection_limiting_max_1_co nnections	Maximum simultaneous connections each connecting IP address is allowed. Set to 0 to disable this limit.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "30"</li></ul>
connection_limiting_max_con nection_rate	Maximum number of new connections each connecting IP address is allowed to make in the rate_timer interval. Set to 0 to disable this limit. If applied to an HTTP Virtual Server each request sent on a connection that is kept alive counts as a new connection. The rate limit is per process: each process within a Traffic Manager accepts new connections from the connecting IP address at this rate. (Each Traffic Manager typically has several processes: one process per available CPU core).  • Type: Ulnt • Required: false • Default value: <none></none>

Property	Description
connection_limiting_min_conn ections	Entry threshold for the max_10_connections limit: the max_10_connections limit is not applied to connecting IP addresses with this many or fewer simultaneous connections. Setting to 0 disables both the max_1_connections and max_10_connections limits, if per_process_connection_count is Yes. (If per_process_connection_count is No, this setting is ignored.)  Type: UInt Required: false Default value: "4"
connection_limiting_rate_time r	How frequently the max_connection_rate is assessed. For example, a value of 1 (second) will impose a limit of max_connection_rate connections per second; a value of 60 will impose a limit of max_connection_rate connections per minute. The valid range is 1-99999 seconds.  • Type: UInt • Required: false • Default value: "60"
debug	<ul> <li>Whether or not to output verbose logging.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
enabled	<ul> <li>Enable or disable this service protection class.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
http_check_rfc2396	Whether or not requests with poorly-formed URLs be should be rejected. This tests URL compliance as defined in RFC2396. Note that enabling this may block some older, non-conforming web browsers.  Type: Boolean Required: false Default value: false
http_max_body_length	Maximum permitted length of HTTP request body data, set to 0 to disable the limit.  Type: UInt Required: false Default value: <none></none>
http_max_header_length	Maximum permitted length of a single HTTP request header (key and value), set to 0 to disable the limit.  Type: UInt Required: false Default value: <none></none>

Property	Description
http_max_request_length	Maximum permitted size of all the HTTP request headers, set to 0 to disable the limit.  Type: UInt Required: false Default value: <none></none>
http_max_url_length	Maximum permitted URL length, set to 0 to disable the limit.  Type: Ulnt Required: false Default value: <none></none>
http_reject_binary	<ul> <li>Whether or not URLs and HTTP request headers that contain binary data (after decoding) should be rejected.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
http_send_error_page	This setting tells the traffic manager to send an HTTP error message if a connection fails the service protection tests, instead of just dropping it. Details of which HTTP response will be sent when particular tests fail can be found in the Help section for this page.  Type: Boolean Required: false
log_time	<ul> <li>Default value: false</li> <li>Log service protection messages at these intervals. If set to 0 no messages will be logged and no alerts will be sent.</li> <li>Type: UInt</li> <li>Required: false</li> <li>Default value: "60"</li> </ul>
note	A description of the service protection class.  Type: String Required: false Default value: <none></none>
per_process_connection_coun t	Whether simultaneous connection counting and limits are per-process. (Each Traffic Manager typically has several processes: one process per available CPU core.) If Yes, a connecting IP address may make that many connections to each process within a Traffic Manager. If No, a connecting IP address may make that many connections to each Traffic Manager as a whole.  • Type: Boolean • Required: false • Default value: false

Property	Description
rule	A TrafficScript rule that will be run on the connection after the service protection criteria have been evaluated. This rule will be executed prior to normal rules configured for the virtual server.
	<ul><li>Type: Reference(config-trafficscript)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
testing	Place the service protection class into testing mode. (Log when this class would have dropped a connection, but allow all connections through).
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

#### vtm\_rate

URI Endpoint: /api/tm/4.0/config/active/rate

A rate shaping class restricts the number of connections being processed by a virtual server at once.

```
# Example usage of vtm_rate resource...
resource "vtm_rate" "my_rate" {
    name = "MyRate"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
max_rate_per_minute	Requests that are associated with this rate class will be rate-shaped to this many requests per minute, set to 0 to disable the limit.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
max_rate_per_second	Although requests will be rate-shaped to the max_rate_per_minute, the traffic manager will also rate limit per-second. This smooths traffic so that a full minute's traffic will not be serviced in the first second of the minute, set this to 0 to disable the per-second limit.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
note	A description of the rate class.
	<ul><li>Type: FreeformString</li><li>Required: false</li><li>Default value: <none></none></li></ul>

#### vtm\_rule

URI Endpoint: /api/tm/4.0/config/active/rules

TrafficScript rules allow traffic inspection and modification.

```
# Example usage of vtm_rule resource...
resource "vtm_rule" "my_rule" {
   content = ""
   name = "MyRule"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
content	Object content
	<ul><li>Type: string</li><li>Required: true</li></ul>

#### vtm\_service\_level\_monitor

URI Endpoint: /api/tm/4.0/config/active/service\_level\_monitors

Service level monitoring is used to produce alerts when an application's performance is degraded. This is done by monitoring the response time of connections to a virtual server.

```
# Example usage of vtm_service_level_monitor resource...
resource "vtm_service_level_monitor" "my_service_level_monitor" {
    name = "MyServiceLevelMonitor"
}
```

Property	Description
name	Name of the object  Type: string Required: true
note	<ul> <li>A description for the SLM class.</li> <li>Type: FreeformString</li> <li>Required: false</li> <li>Default value: <none></none></li> </ul>
response_time	Responses that arrive within this time limit, expressed in milliseconds, are treated as conforming.  Type: UInt Required: false Default value: "1000"

Property	Description
serious_threshold	When the percentage of conforming responses drops below this level, a serious error level message will be emitted.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
warning_threshold	When the percentage of conforming responses drops below this level, a warning message will be emitted.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "50"</li></ul>

### vtm\_ssl\_client\_key

URI Endpoint: /api/tm/4.0/config/active/ssl/client\_keys

SSL Client Certificates are used when connecting to backend nodes that require client certificate authentication.

```
# Example usage of vtm_ssl_client_key resource...
resource "vtm_ssl_client_key" "my_ssl_client_key" {
   name = "MySslClientKey"
   note =
   private =
   public =
   request =
}
```

Property	Description
name	Name of the object  Type: string Required: true
note	Notes for this certificate  Type: FreeformString Required: true Default value: <none></none>
private	Private key for certificate  Type: FreeformString Required: true Default value: <none></none>

Property	Description
public	Public certificate
	<ul><li>Type: FreeformString</li><li>Required: true</li><li>Default value: <none></none></li></ul>
request	Certificate Signing Request for certificate
	<ul><li>Type: FreeformString</li><li>Required: true</li><li>Default value: <none></none></li></ul>

#### vtm\_ssl\_server\_key

URI Endpoint: /api/tm/4.0/config/active/ssl/server\_keys

SSL Server Certificates are presented to clients by virtual servers when SSL decryption is enabled.

```
# Example usage of vtm_ssl_server_key resource...
resource "vtm_ssl_server_key" "my_ssl_server_key" {
   name = "MySslServerKey"
   note =
   private =
   public =
   request =
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
note	Notes for this certificate
	<ul><li>Type: FreeformString</li><li>Required: true</li><li>Default value: <none></none></li></ul>
private	Private key for certificate
	<ul><li>Type: FreeformString</li><li>Required: true</li><li>Default value: <none></none></li></ul>
public	Public certificate
	<ul><li>Type: FreeformString</li><li>Required: true</li><li>Default value: <none></none></li></ul>
request	Certificate Signing Request for certificate
	<ul><li>Type: FreeformString</li><li>Required: true</li><li>Default value: <none></none></li></ul>

#### vtm ssl ca

URI Endpoint: /api/tm/4.0/config/active/ssl/cas

SSL certificate authority certificates (CAs) and certificate revocation lists (CRLs) can be used when validating server and client certificates.

```
# Example usage of vtm_ssl_ca resource...
resource "vtm_ssl_ca" "my_ssl_ca" {
    content = ""
    name = "MySslCa"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
content	Object content
	<ul><li>Type: string</li><li>Required: true</li></ul>

#### vtm\_security

URI Endpoint: /api/tm/4.0/config/active/security

Security settings that restrict remote administration for the cluster. Additional security options can be found in Global Settings.

```
# Example usage of vtm_security resource...
resource "vtm_security" "my_security" {
}
```

Property	Description
access	Access to the admin server and REST API is restricted by usernames and passwords. You can further restrict access to just trusted IP addresses, CIDR IP subnets or DNS wildcards. These access restrictions are also used when another traffic manager initially joins the cluster, after joining the cluster these restrictions are no longer used. Care must be taken when changing this setting, as it can cause the administration server to become inaccessible. Access to the admin UI will not be affected until it is restarted.  Type: Set(String) Required: false Default value: <none></none>
ssh_intrusion_bantime	The amount of time in seconds to ban an offending host for.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "600"</li></ul>
ssh_intrusion_blacklist	The list of hosts to permanently ban, identified by IP address or DNS hostname in a space-separated list.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssh_intrusion_enabled	Whether or not the SSH Intrusion Prevention tool is enabled.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssh_intrusion_findtime	The window of time in seconds the maximum number of connection attempts applies to. More than (maxretry) failed attempts in this time span will trigger a ban.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "600"</li></ul>
ssh_intrusion_maxretry	The number of failed connection attempts a host can make before being banned.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "6"</li></ul>
ssh_intrusion_whitelist	The list of hosts to never ban, identified by IP address, DNS hostname or subnet mask, in a space-separated list.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>

## vtm\_persistence

URI Endpoint: /api/tm/4.0/config/active/persistence

A session persistence class is used to identify the session a new connection belongs too and deliver it to the same backend node.

```
# Example usage of vtm_persistence resource...
resource "vtm_persistence" "my_persistence" {
    name = "MyPersistence"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
cookie	The cookie name to use for tracking session persistence.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
delete	Whether or not the session should be deleted when a session failure occurs. (Note, setting a failure mode of 'choose a new node' implicitly deletes the session.)
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
failure_mode	The action the pool should take if the session data is invalid or it cannot contact the node specified by the session.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "new_node"</li> <li>Permitted values:         "close": Close the connection (using error_file on Virtual Servers &gt;         Edit &gt; Protocol Settings)</li> </ul>
	"new_node": Choose a new node to use
	"url": Redirect the user to a given URL
note	A description of the session persistence class.
	<ul><li>Type: FreeformString</li><li>Required: false</li><li>Default value: <none></none></li></ul>
subnet_prefix_length_v4	When using IP-based session persistence, ensure all requests from this IPv4 subnet, specified as a prefix length, are sent to the same node. If set to 0, requests from different IPv4 addresses will be load-balanced individually.  Type: Int Required: false Default value: <none></none>

Property	Description
subnet_prefix_length_v6	When using IP-based session persistence, ensure all requests from this IPv6 subnet, specified as a prefix length, are sent to the same node. If set to 0, requests from different IPv6 addresses will be load-balanced individually.
	<ul><li>Type: Int</li><li>Required: false</li><li>Default value: <none></none></li></ul>
type	The type of session persistence to use.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "ip"</li> <li>Permitted values:     "asp": ASP and ASP.NET session persistence</li> </ul>
	"cookie": Monitor application cookies
	"ip": IP-based persistence
	"j2ee": J2EE session persistence
	"named": Named Node session persistence
	"ssl": SSL Session ID persistence
	"transparent": Transparent session affinity
	"universal": Universal session persistence
	"x_zeus": X-Zeus-Backend cookies
url	The redirect URL to send clients to if the session persistence is configured to redirect users when a node dies.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>

## $vtm\_traffic\_ip\_group$

URI Endpoint: /api/tm/4.0/config/active/traffic\_ip\_groups

Traffic IP groups are sets of IP addresses that are distributed across a cluster for fault tolerance.

```
# Example usage of vtm_traffic_ip_group resource...
resource "vtm_traffic_ip_group" "my_traffic_ip_group" {
    name = "MyTrafficIpGroup"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
backend_traffic_ips	IP addresses associated with the Traffic IP group that can be used for communication with back-end servers.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
enabled	If set to No, the traffic IP group will be disabled and none of the traffic IP addresses will be raised.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
hash_source_port	Whether or not the source port should be taken into account when deciding which traffic manager should handle a request.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ip_assignment_mode	Configure how traffic IPs are assigned to traffic managers in Single- Hosted mode
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "balanced"</li> <li>Permitted values:         <ul> <li>"alphabetic": Alphabetical order of traffic manager hostnames</li> </ul> </li> </ul>
	"balanced": Approximately balanced between traffic managers
ip_mapping	A table assigning traffic IP addresses to machines that should host them. Traffic IP addresses not specified in this table will automatically be assigned to a machine.  • Type: Table
	<ul> <li>Required: false</li> <li>Primary key:         <ul> <li>ip (String): A traffic IP address (from the ipaddresses property). (Required)</li> </ul> </li> <li>Sub keys:         <ul> <li>traffic_manager (String): The name of the traffic manager that</li> </ul> </li> </ul>
in managing to a	should host the IP address.
ip_mapping_json	A Traffic Manager REST-compatible JSON representation of the "ip_mapping" table property. Use this field with the "vtm_traffic_ip_group_ip_mapping_table" data source for dynamic table generation from input variables.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
ipaddresses	The IP addresses that belong to the Traffic IP group.  Type: Set(String) Required: false Default value: <none></none>
keeptogether	If set to Yes then all the traffic IPs will be raised on a single traffic manager. By default they're distributed across all active traffic managers in the traffic IP group.  Type: Boolean Required: false Default value: false
location	The location in which the Traffic IP group is based.  Type: Int Required: false Default value: <none></none>
machines	The traffic managers that can host the traffic IP group's IP addresses.  • Type: Set(Reference(config-tm))  • Required: false  • Default value: <none></none>
mode	The method used to distribute traffic IPs across machines in the cluster. If "multihosted" is used then multicast must be set to an appropriate multicast IP address.  Type: Enum(String) Required: false Default value: "singlehosted" Permitted values: "ec2elastic": Use an EC2-Classic Elastic IP address. "ec2vpcelastic": Use an EC2-VPC Elastic IP address. "ec2vpcprivate": Use an EC2-VPC Private IP address. "multihosted": Raise each address on every machine in the group (Multi-Hosted mode) - IPv4 only "rhi": Use route health injection to route traffic to the active machine - IPv4 only "singlehosted": Raise each address on a single machine (Single-Hosted mode)
multicast	The multicast IP address used to duplicate traffic to all traffic managers in the group.  Type: String Required: false Default value: <none></none>
note	A note, used to describe this Traffic IP Group  Type: String Required: false Default value: <none></none>

Property	Description
rhi_bgp_metric_base	The base BGP routing metric for this Traffic IP group. This is the advertised routing cost for the active traffic manager in the cluster. It can be used to set up inter-cluster failover.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>
rhi_bgp_passive_metric_offset	The BGP routing metric offset for this Traffic IP group. This is the difference between the advertised routing cost for the active and passive traffic manager in the cluster.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>
rhi_ospfv2_metric_base	The base OSPFv2 routing metric for this Traffic IP group. This is the advertised routing cost for the active traffic manager in the cluster. It can be used to set up inter-cluster failover.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>
rhi_ospfv2_passive_metric_off set	The OSPFv2 routing metric offset for this Traffic IP group. This is the difference between the advertised routing cost for the active and passive traffic manager in the cluster.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>
rhi_protocols	A list of protocols to be used for RHI. Currently must be 'ospf' or 'bgp' or both. The default, if empty, is 'ospf', which means that it is not possible to specify no protocol.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "ospf"</li></ul>
slaves	A list of traffic managers that are in 'passive' mode. This means that in a fully working environment, they will not have any traffic IP addresses assigned to them.
	<ul><li>Type: Set(Reference(config-tm))</li><li>Required: false</li><li>Default value: <none></none></li></ul>

# vtm\_traffic\_manager

URI Endpoint: /api/tm/4.0/config/active/traffic\_managers

The conf/zxtms directory contains a configuration file for each traffic manager in your cluster. The name of each file is the hostname of the traffic manager it represents. These files contain host-specific configuration data and on each installation of the software, the conf/../global.cfg file is sym-linked to the host's own configuration in the conf/zxtms directory. The files may contain a variety of configuration options that are configured in various locations under the System section of the Admin Server UI and the System section of the SOAP API and CLI.

```
# Example usage of vtm_traffic_manager resource...
resource "vtm_traffic_manager" "my_traffic_manager" {
    name = "MyTrafficManager"
}
```

Property	Description
name	Name of the object  Type: string Required: true
adminmasterxmlip	The Application Firewall master XML IP.  Type: String Required: false Default value: "0.0.0.0"
adminslavexmlip	The Application Firewall slave XML IP.  Type: String Required: false Default value: "0.0.0.0"
appliance_card	<ul> <li>The table of network cards of a hardware appliance</li> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>name (String): Network card PCI ID (Required)</li> </ul> </li> <li>Sub keys: <ul> <li>interfaces (List(String)): The order of the interfaces of a network card</li> <li>label (String): The labels of the installed network cards</li> </ul> </li> </ul>
appliance_card_json	A Traffic Manager REST-compatible JSON representation of the "appliance_card" table property. Use this field with the "vtm_traffic_manager_appliance_card_table" data source for dynamic table generation from input variables.  Type: String Required: false Default value: <none></none>
appliance_gateway_ipv4	The default gateway.  Type: String Required: false Default value: <none></none>

Property	Description
appliance_gateway_ipv6	The default IPv6 gateway.  Type: String Required: false Default value: <none></none>
appliance_hostname	Name (hostname.domainname) of the appliance.  Type: String Required: false Default value: <none></none>
appliance_hosts	A table of hostname to static ip address mappings, to be placed in the / etc/hosts file.  Type: Table Required: false Primary key: name (String): The name of a host. (Required) Sub keys: ip_address (String): The static IP address of the host.
appliance_hosts_json	A Traffic Manager REST-compatible JSON representation of the "appliance_hosts" table property. Use this field with the "vtm_traffic_manager_hosts_table" data source for dynamic table generation from input variables.  Type: String Required: false Default value: <none></none>

Property	Description
appliance_if	A table of network interface specific settings.  Type: Table Required: false Primary key: name (String): A network interface name. (Required) Sub keys: utoneg (Boolean): Whether auto-negotiation should be enabled for the interface. bmode (Enum(String)): The trunking mode used for the interface (only 802.3ad is currently supported). Permitted values: "802_3ad": IEEE 802.3ad "balance_alb": Adaptive Load Balancing bond (String): The trunk of which the interface should be a member. duplex (Boolean): Whether full-duplex should be enabled for the interface. mode (Enum(String)): Set the configuriation mode of an interface, the interface name is used in place of the * (asterisk). Permitted values: "dhcp": DHCP "static": Static mtu (UInt): The maximum transmission unit (MTU) of the interface. speed (Enum(String)): The speed of the interface. Permitted values: "10": 10Mbs "100": 10Gbs "10000": 10Gbs "100000": 40Gbs
appliance_if_json	A Traffic Manager REST-compatible JSON representation of the "appliance_if" table property. Use this field with the "vtm_traffic_manager_if_table" data source for dynamic table generation from input variables.  • Type: String • Required: false • Default value: <none></none>

Property	Description
appliance_ip	A table of network interfaces and their network settings.  Type: Table Required: false Primary key: name (String): A network interface name. (Required) Sub keys: addr (String): The IP address for the interface. isexternal (Boolean): Whether the interface is externally facing. mask (String): The IP mask (netmask) for the interface.
appliance_ip_json	A Traffic Manager REST-compatible JSON representation of the "appliance_ip" table property. Use this field with the "vtm_traffic_manager_ip_table" data source for dynamic table generation from input variables.  Type: String Required: false Default value: <none></none>
appliance_ipmi_lan_access	<ul> <li>Whether IPMI LAN access should be enabled or not.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
appliance_ipmi_lan_addr	The IP address of the appliance IPMI LAN channel.  • Type: String  • Required: false  • Default value: <none></none>
appliance_ipmi_lan_gateway	The default gateway of the IPMI LAN channel.  Type: String Required: false Default value: <none></none>
appliance_ipmi_lan_ipsrc	The addressing mode the IPMI LAN channel operates.  Type: Enum(String) Required: false Default value: "static" Permitted values: "dhcp": Address obtained by DHCP "static": Static IP Address
appliance_ipmi_lan_mask	Set the IP netmask for the IPMI LAN channel.  Type: String Required: false Default value: <none></none>
appliance_ipv4_forwarding	<ul> <li>Whether or not IPv4 forwarding is enabled.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>

Property	Description
appliance_ipv6_forwarding	<ul> <li>Whether or not IPv6 forwarding is enabled.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
appliance_licence_agreed	<ul> <li>Whether or not the license agreement has been accepted. This determines whether or not the Initial Configuration wizard is displayed.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
appliance_manageazureroute s	<ul> <li>Whether or not the software manages the Azure policy routing.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
appliance_managedpa	Whether or not the software manages the system configuration based on Data Plane Acceleration mode  Type: Boolean Required: false Default value: false
appliance_manageec2conf	<ul> <li>Whether or not the software manages the EC2 config.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
appliance_manageiptrans	<ul> <li>Whether or not the software manages the IP transparency</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
appliance_managereturnpath	Whether or not the software manages return path routing. If disabled, the appliance won't modify iptables / rules / routes for this feature.  Type: Boolean Required: false Default value: false
appliance_managevpcconf	<ul> <li>Whether or not the software manages the EC2-VPC secondary IPs.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
appliance_name_servers	The IP addresses of the nameservers the appliance should use and place in /etc/resolv.conf.  Type: Set(String) Required: false Default value: <none></none>

Property	Description
appliance_ntpservers	The NTP servers the appliance should use to synchronize its clock.
	<ul> <li>Type: List(String)</li> <li>Required: false</li> <li>Default value: "0.zeus.pool.ntp.org 1.zeus.pool.ntp.org 2.zeus.pool.ntp.org 3.zeus.pool.ntp.org"</li> </ul>
appliance_routes	A table of destination IP addresses and routing details to reach them.
	<ul> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>name (String): A destination IP address. (Required)</li> </ul> </li> <li>Sub keys: <ul> <li>gw (String): The gateway IP to configure for the route.</li> <li>if (String): The network interface to configure for the route.</li> <li>mask (String): The netmask to apply to the IP address.</li> </ul> </li> </ul>
appliance_routes_json	A Traffic Manager REST-compatible JSON representation of the "appliance_routes" table property. Use this field with the "vtm_traffic_manager_routes_table" data source for dynamic table generation from input variables.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
appliance_search_domains	The search domains the appliance should use and place in /etc/ resolv.conf.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
appliance_shim_client_id	The client ID provided by the portal for this server.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
appliance_shim_client_key	The client key provided by the portal for this server.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
appliance_shim_enabled	Enable the Riverbed Cloud SteelHead discovery agent on this appliance.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
appliance_shim_ips	The IP addresses of the Riverbed Cloud SteelHeads to use, as a space or comma separated list. If using priority load balancing this should be in ascending order of priority (highest priority last).
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
appliance_shim_load_balance	The load balancing method for selecting a Riverbed Cloud SteelHead appliance.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "round_robin"</li> <li>Permitted values:    "priority": Priority</li> </ul>
	"round_robin": Round Robin
appliance_shim_log_level	The minimum severity that the discovery agent will record to its log.
	<ul> <li>Type: Enum(UInt)</li> <li>Required: false</li> <li>Default value: "notice"</li> <li>Permitted values: "critical": Log critical errors</li> </ul>
	"debug": Log debug or more severe errors (all errors)
	"info": Log info or more severe errors
	"notice": Log notice or more severe errors
	"serious": Log serious or more severe errors
	"warning": Log warning or more severe errors
appliance_shim_mode	The mode used to discover Riverbed Cloud SteelHeads in the local cloud or data center.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "portal"</li> <li>Permitted values: "local": Local Portal</li> </ul>
	"manual": Manual
	"portal": Riverbed Portal
appliance_shim_portal_url	The hostname or IP address of the local portal to use.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
appliance_shim_proxy_host	The IP or hostname of the proxy server to use to connect to the portal. Leave blank to not use a proxy server.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
appliance_shim_proxy_port	The port of the proxy server, must be set if a proxy server has been configured.  Type: String Required: false Default value: <none></none>

Property	Description
appliance_ssh_enabled	Whether or not the SSH server is enabled on the appliance.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
appliance_ssh_password_allo	Whether or not the SSH server allows password based login.
wed	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
appliance_ssh_port	The port that the SSH server should listen on.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "22"</li></ul>
appliance_sysctl	Custom kernel parameters applied by the user with sysctl interface
	<ul> <li>Type: Table</li> <li>Required: false</li> <li>Primary key:         <ul> <li>sysctl (String): The name of the kernel parameter, e.g. net.ipv4.forward (Required)</li> </ul> </li> <li>Sub keys:         <ul> <li>description (String): Associated optional description for the sysctl</li> <li>value (String): The value of the kernel parameter</li> </ul> </li> </ul>
appliance_sysctl_json	A Traffic Manager REST-compatible JSON representation of the "appliance_sysctl" table property. Use this field with the "vtm_traffic_manager_appliance_sysctl_table" data source for dynamic table generation from input variables.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
appliance_timezone	The timezone the appliance should use. This must be a path to a timezone file that exists under /usr/share/zoneinfo/.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "US/Pacific"</li></ul>
appliance_vlans	The VLANs the software should raise. A VLAN should be configured using the format <dev>.<vlanid>, where <dev> is the name of a network device that exists in the host system, eth0.100 for example.  Type: Set(String) Required: false Default value: <none></none></dev></vlanid></dev>
authenticationserverip	The Application Firewall Authentication Server IP.  Type: String Required: false Default value: "0.0.0.0"

Property	Description
cloud_platform	Cloud platform where the traffic manager is running.  Type: String Required: false Default value: <none></none>
cluster_comms_allow_update	Whether or not this instance of the software can send configuration updates to other members of the cluster. When not clustered this key is ignored. When clustered the value can only be changed by another machine in the cluster that has allow_update set to true. If set to false then it will not be possible to log into the admin server for this instance.  • Type: Boolean • Required: false • Default value: false
cluster_comms_bind_ip	The IP address that the software should bind to for internal administration communications. See also port. If the software is not part of a cluster the default is to use 127.0.0.1 and there should be no reason to touch this setting. If the software is part of a cluster then the default is to listen on all raised IPs, in this case an alternative configuration is to listen on a single IP address. This may be useful if you have a separate management network and wish to restrict control messages to it. It is important to ensure that the allowed_update_hosts (in the Global Settings resource) is compatible with the IP configured here.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "*"</li></ul>
cluster_comms_external_ip	This is the optional external ip of the traffic manager, which is used to circumvent natting when traffic managers in a cluster span different networks.  Type: String Required: false Default value: <none></none>
cluster_comms_port	The port that the software should listen on for internal administration communications. See also bind_ip.  • Type: UInt • Required: false • Default value: "9080"
ec2_trafficips_public_enis	List of MAC addresses of interfaces which the traffic manager can use to associate the EC2 elastic IPs (Traffic IPs) to the instance.  • Type: Set(String)  • Required: false  • Default value: <none></none>

Property	Description
fault_tolerance_bgp_router_id	The BGP router id If set to empty, then the IPv4 address used to communicate with the default IPv4 gateway is used instead. Specifying 0.0.0.0 will stop the traffic manager routing software from running the BGP protocol.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
fault_tolerance_lss_dedicated_ips	IP addresses associated with the links dedicated by the user for receiving L4 state sync messages from other peers in a cluster.
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
fault_tolerance_ospfv2_ip	The traffic manager's permanent IPv4 address which the routing software will use for peering and transit traffic, and as its OSPF router ID. If set to empty, then the address used to communicate with the default IPv4 gateway is used instead. Specifying 0.0.0.0 will stop the traffic manager routing software from running the OSPF protocol.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
fault_tolerance_ospfv2_neighb or_addrs	The IP addresses of routers which are expected to be found as OSPFv2 neighbors of the traffic manager. A warning will be reported if some of the expected routers are not peered, and an error will be reported if none of the expected routers are peered. An empty list disables monitoring. The special value %gateway% is a placeholder for the default gateway.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: "%gateway%"</li></ul>
iptables_config_enabled	Whether the Traffic Manager should configure the iptables built-in chains to call Traffic Manager defined rules (e.g. the IP transparency chain). This should only be disabled in case of conflict with other software that manages iptables, e.g. firewalls. When disabled, you will need to add rules manually to use these features - see the user manual for details.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
iptrans_fwmark	The netfilter forwarding mark to use for IP transparency rules  Type: UInt Required: false Default value: "320"

Property	Description
iptrans_iptables_enabled	Whether IP transparency may be used via netfilter/iptables. This requires Linux 2.6.24 and the iptables socket extension. For older Linux versions, the "ztrans" kernel module may be used instead.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
iptrans_routing_table	The special routing table ID to use for IP transparency rules  Type: UInt Required: false Default value: "320"
java_port	The port the Java Extension handler process should listen on. This port will be bound for localhost communications only.  Type: UInt Required: false Default value: "9060"
location	This is the location of the local traffic manager is in.  Type: String Required: false Default value: <none></none>
nameip	Replace Traffic Manager name with an IP address.  Type: String Required: false Default value: <none></none>
num_aptimizer_threads	How many worker threads the Web Accelerator process should create to optimise content. By default, one thread will be created for each CPU on the system.  Type: UInt Required: false Default value: <none></none>
num_children	The number of worker processes the software will run. By default, one child process will be created for each CPU on the system. You may wish to reduce this to effectively "reserve" CPU(s) for other processes running on the host system.  Type: UInt Required: false Default value: <none></none>
numberofcpus	The number of Application Firewall decider process to run.  Type: Ulnt Required: false Default value: <none></none>
remote_licensing_email_addre ss	The e-mail address sent as part of a remote licensing request.  Type: String Required: false Default value: <none></none>

Property	Description
remote_licensing_message	<ul> <li>A free-text field sent as part of a remote licensing request.</li> <li>Type: String</li> <li>Required: false</li> <li>Default value: <none></none></li> </ul>
rest_api_bind_ips	A list of IP Addresses which the REST API will listen on for connections. The list should contain IP addresses (IPv4 or IPv6) or a single entry containing an asterisk (*). This indicates that the REST API should listen on all IP Addresses.  Type: Set(String) Required: false Default value: "*"
rest_api_port	The port on which the REST API should listen for requests.  Type: UInt Required: false Default value: "9070"
restserverport	The Application Firewall REST Internal API port, this port should not be accessed directly  Type: UInt Required: false Default value: <none></none>
snmp_allow	Restrict which IP addresses can access the SNMP command responder service. The value can be all, localhost, or a list of IP CIDR subnet masks. For example 10.100.0.0/16 would allow connections from any IP address beginning with 10.100.  Type: Set(String) Required: false Default value: "all"
snmp_auth_password	The authentication password. Required (minimum length 8 characters) if security_level includes authentication.  Type: Password Required: false Default value: <none></none>
snmp_bind_ip	The IP address the SNMP service should bind its listen port to. The value * (asterisk) means SNMP will listen on all IP addresses.  • Type: String  • Required: false  • Default value: "*"
snmp_community	The community string required for SNMPv1 and SNMPv2c commands. (If empty, all SNMPv1 and SNMPv2c commands will be rejected).  • Type: String  • Required: false  • Default value: "public"

Property	Description
snmp_enabled	Whether or not the SNMP command responder service should be enabled on this traffic manager.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
snmp_hash_algorithm	The hash algorithm for authenticated SNMPv3 communications.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "md5"</li> <li>Permitted values: "md5": MD5</li> </ul>
	"sha1": SHA-1
snmp_port	The port the SNMP command responder service should listen on. The value default denotes port 161 if the software is running with root privileges, and 1161 otherwise.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "default"</li></ul>
snmp_priv_password	The privacy password. Required (minimum length 8 characters) if security_level includes privacy (message encryption).
	<ul><li>Type: Password</li><li>Required: false</li><li>Default value: <none></none></li></ul>
snmp_security_level	The security level for SNMPv3 communications.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "noauthnopriv"</li> <li>Permitted values: "authnopriv": Authentication only</li> </ul>
	"authpriv": Authentication and Privacy
	"noauthnopriv": No Authentication, No Privacy
snmp_username	The username required for SNMPv3 commands. (If empty, all SNMPv3 commands will be rejected).  • Type: String  • Required: false  • Default value: <none></none>

Property	Description
trafficip	A table mapping interfaces to networks, used by the traffic manager to select which interface to raise a Traffic IP on.
	<ul> <li>Type: Table</li> <li>Required: false</li> <li>Primary key:         <ul> <li>name (String): A network interface. (Required)</li> </ul> </li> <li>Sub keys:         <ul> <li>networks (Set(String)): A set of IP/masks to which the network interface maps.</li> </ul> </li> </ul>
trafficip_json	A Traffic Manager REST-compatible JSON representation of the "trafficip" table property. Use this field with the "vtm_traffic_manager_trafficip_table" data source for dynamic table generation from input variables.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
updaterip	The Application Firewall Updater IP.  Type: String Required: false Default value: "0.0.0.0"

## vtm\_rule\_authenticator

URI Endpoint: /api/tm/4.0/config/active/rule\_authenticators

TrafficScript authenticators define remote authentication services that can be queried via a TrafficScript rule.

```
# Example usage of vtm_rule_authenticator resource...
resource "vtm_rule_authenticator" "my_rule_authenticator" {
    name = "MyRuleAuthenticator"
}
```

Property	Description
name	Name of the object  Type: string Required: true
host	The hostname or IP address of the remote authenticator.  Type: String Required: false Default value: <none></none>
ldap_attributes	A list of attributes to return from the search. If blank, no attributes will be returned. If set to '*' then all user attributes will be returned.  Type: Set(String) Required: false Default value: <none></none>

Property	Description
ldap_bind_dn	The distinguished name (DN) of the 'bind' user. The traffic manager will connect to the LDAP server as this user when searching for user records.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ldap_bind_password	The password for the bind user.
	<ul><li>Type: Password</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ldap_filter	The filter used to locate the LDAP record for the user being authenticated. Any occurrences of '%u' in the filter will be replaced by the name of the user being authenticated.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ldap_filter_base_dn	The base distinguished name (DN) under which user records are located on the server.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ldap_ssl_cert	The SSL certificate that the traffic manager should use to validate the remote server. If no certificate is specified then no signature validation will be performed.
	<ul> <li>Type: Reference(config-ssl-cacrl)</li> <li>Required: false</li> <li>Default value: <none></none></li> </ul>
ldap_ssl_enabled	Whether or not to enable SSL encryption to the LDAP server.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ldap_ssl_type	The type of LDAP SSL encryption to use.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "Idaps"</li> <li>Permitted values:     "Idaps": LDAPS</li> <li>"starttls": Start TLS</li> </ul>

Property	Description
note	<ul> <li>A description of the authenticator.</li> <li>Type: FreeformString</li> <li>Required: false</li> <li>Default value: <none></none></li> </ul>
port	The port on which the remote authenticator should be contacted.  Type: Ulnt Required: false Default value: "389"

## vtm\_user\_authenticator

URI Endpoint: /api/tm/4.0/config/active/user\_authenticators

A user authenticator is used to allow access to the UI and REST API by querying a remote authentication service.

```
# Example usage of vtm_user_authenticator resource...
resource "vtm_user_authenticator" "my_user_authenticator" {
   name = "MyUserAuthenticator"
   type =
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
description	A description of the authenticator.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
enabled	Whether or not this authenticator is enabled.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ldap_base_dn	The base DN (Distinguished Name) under which directory searches will be applied. The entries for your users should all appear under this DN. An example of a typical base DN is: OU=users, DC=mycompany, DC=local
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
ldap_bind_dn	Template to construct the bind DN (Distinguished Name) from the username. The string %u will be replaced by the username. Examples: %u@mycompany.local for Active Directory or cn=%u, dc=mycompany, dc=local for both LDAP and Active Directory.  Type: String Required: false Default value: <none></none>
ldap_dn_method	The bind DN (Distinguished Name) for a user can either be searched for in the directory using the base distinguished name and filter values, or it can be constructed from the username.  Type: Enum(String) Required: false Default value: "none" Permitted values:
	"construct": Construct  "none": No setting configured  "search": Search
ldap_fallback_group	If the group attribute is not defined, or returns no results for the user logging in, the group named here will be used. If not specified, users will be denied access to the traffic manager if no groups matching a Permission Group can be found for them in the directory.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ldap_filter	A filter that can be used to extract a unique user record located under the base DN (Distinguished Name). The string %u will be replaced by the username. This filter is used to find a user's bind DN when dn_method is set to "Search", and to extract group information if the group filter is not specified. Examples: sAMAccountName=%u for Active Directory, or uid=%u for some Unix LDAP schemas.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ldap_group_attribute	The LDAP attribute that gives a user's group. If there are multiple entries for the attribute all will be extracted and they'll be lexicographically sorted, then the first one to match a Permission Group name will be used.  Type: String Required: false Default value: <none></none>

Property	Description
ldap_group_field	The sub-field of the group attribute that gives a user's group. For example, if group_attribute is memberOf and this retrieves values of the form CN=mygroup, OU=groups, OU=users, DC=mycompany, DC=local you would set group_field to CN. If there are multiple matching fields only the first matching field will be used.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ldap_group_filter	If the user record returned by filter does not contain the required group information you may specify an alternative group search filter here. This will usually be required if you have Unix/POSIX-style user records. If multiple records are returned the list of group names will be extracted from all of them. The string %u will be replaced by the username. Example: (&(memberUid=%u)(objectClass=posixGroup))
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ldap_port	The port to connect to the LDAP server on.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "389"</li></ul>
ldap_search_dn	The bind DN (Distinguished Name) to use when searching the directory for a user's bind DN. You can leave this blank if it is possible to perform the bind DN search using an anonymous bind.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ldap_search_password	If binding to the LDAP server using search_dn requires a password, enter it here.
	<ul><li>Type: Password</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ldap_server	The IP or hostname of the LDAP server.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ldap_timeout	Connection timeout in seconds.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "30"</li></ul>
radius_fallback_group	If no group is found using the vendor and group identifiers, or the group found is not valid, the group specified here will be used.  • Type: String • Required: false • Default value: <none></none>

Property	Description
radius_group_attribute	The RADIUS identifier for the attribute that specifies an account's group. May be left blank if fallback group is specified.  • Type: UInt • Required: false
	Default value: "1"
radius_group_vendor	The RADIUS identifier for the vendor of the RADIUS attribute that specifies an account's group. Leave blank if using a standard attribute (i.e. for Filter-Id set group_attribute to 11).
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "7146"</li></ul>
radius_nas_identifier	This value is sent to the RADIUS server.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
radius_nas_ip_address	This value is sent to the RADIUS server, if left blank the address of the interfaced used to connect to the server will be used.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
radius_port	The port to connect to the RADIUS server on.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "1812"</li></ul>
radius_secret	Secret key shared with the RADIUS server.
	<ul><li>Type: Password</li><li>Required: false</li><li>Default value: <none></none></li></ul>
radius_server	The IP or hostname of the RADIUS server.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
radius_timeout	Connection timeout in seconds.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "30"</li></ul>
tacacs_plus_auth_type	Authentication type to use.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "pap"</li> <li>Permitted values:     "ascii": ASCII</li> </ul>
	"pap": PAP

Property	Description
tacacs_plus_fallback_group	If group_service is not used, or no group value is provided for the user by the TACACS+ server, the group specified here will be used. If this is not specified, users with no TACACS+ defined group will be denied access.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
tacacs_plus_group_field	The TACACS+ "service" field that provides each user's group.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "permission-group"</li></ul>
tacacs_plus_group_service	The TACACS+ "service" that provides each user's group field.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "zeus"</li></ul>
tacacs_plus_port	The port to connect to the TACACS+ server on.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "49"</li></ul>
tacacs_plus_secret	Secret key shared with the TACACS+ server.
	<ul><li>Type: Password</li><li>Required: false</li><li>Default value: <none></none></li></ul>
tacacs_plus_server	The IP or hostname of the TACACS+ server.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
tacacs_plus_timeout	Connection timeout in seconds.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "30"</li></ul>
type	The type and protocol used by this authentication service.
	<ul> <li>Type: Enum(String)</li> <li>Required: true</li> <li>Default value: <none></none></li> <li>Permitted values:     "Idap": LDAP     "radius": RADIUS     "tacacs_plus": TACACS+</li> </ul>

## vtm\_user\_group

URI Endpoint: /api/tm/4.0/config/active/user\_groups

Permission groups specify permissions for groups of users. These groups can be given read-write or read-only access to different parts of the configuration hierarchy. Each group will contain a table of permissions. Each table entry has a name that corresponds to a part of the configuration hierarchy, and a corresponding access level. The access level may have values of either none, ro (read only, this is the default), or full. Some permissions have sub-permissions, these are denoted by following the parent permission name with a colon (:) followed by the sub-permission name. The built-in admin group has a special permission key of all with the value full, this must not be altered for the admin group but can be used in other group configuration files to change the default permission level for the group.

```
# Example usage of vtm_user_group resource...
resource "vtm_user_group" "my_user_group" {
    name = "MyUserGroup"
}
```

Property	Description
name	Name of the object  Type: string Required: true
description	A description for the group.  Type: String Required: false Default value: <none></none>
password_expire_time	Members of this group must renew their passwords after this number of days. To disable password expiry for the group set this to 0 (zero). Note that this setting applies only to local users.  Type: UInt Required: false Default value: <none></none>
permissions	A table defining which level of permission this group has for specific configuration elements.  Type: Table Required: false Primary key: name (String): Configuration element to which this group has a level of permission. (Required) Sub keys: access_level (String): Permission level for the configuration element (none, ro or full)

Property	Description
permissions_json	A Traffic Manager REST-compatible JSON representation of the "permissions" table property. Use this field with the "vtm_user_group_permissions_table" data source for dynamic table generation from input variables.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
timeout	Inactive UI sessions will timeout after this number of seconds. To disable inactivity timeouts for the group set this to 0 (zero).
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "30"</li></ul>

## vtm\_virtual\_server

URI Endpoint: /api/tm/4.0/config/active/virtual\_servers

The conf/vservers directory contains configuration files that define virtual servers. The name of a file is the name of the virtual server it defines. Virtual servers can be configured under the Services > Virtual Servers section of the Admin Server UI or by using functions under the VirtualServer section of the SOAP API and CLI.

```
# Example usage of vtm_virtual_server resource...
resource "vtm_virtual_server" "my_virtual_server" {
   name = "MyVirtualServer"
   pool =
   port =
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
add_cluster_ip	Whether or not the virtual server should add an "X-Cluster-Client-Ip" header to the request that contains the remote client's IP address.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
add_x_forwarded_for	Whether or not the virtual server should append the remote client's IP address to the X-Forwarded-For header. If the header does not exist, it will be added.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

Property	Description
add_x_forwarded_proto	Whether or not the virtual server should add an "X-Forwarded-Proto" header to the request that contains the original protocol used by the client to connect to the traffic manager.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
aptimizer_enabled	Whether the virtual server should optimize web content.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
aptimizer_profile	A table of Aptimizer profiles and the application scopes that apply to them.
	<ul> <li>Type: Table</li> <li>Required: false</li> <li>Primary key:         <ul> <li>name (String): The name of an Aptimizer acceleration profile. (Required)</li> </ul> </li> <li>Sub keys:         <ul> <li>urls (Set(String)): The application scopes which apply to the acceleration profile.</li> </ul> </li> </ul>
aptimizer_profile_json	A Traffic Manager REST-compatible JSON representation of the "aptimizer_profile" table property. Use this field with the "vtm_virtual_server_profile_table" data source for dynamic table generation from input variables.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
autodetect_upgrade_headers	Whether the traffic manager should check for HTTP responses that confirm an HTTP connection is transitioning to the WebSockets protocol. If that such a response is detected, the traffic manager will cease any protocol-specific processing on the connection and just pass incoming data to the client/server as appropriate.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
bandwidth_class	The bandwidth management class that this server should use, if any.
	<ul><li>Type: Reference(config-bandwidth)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
bypass_data_plane_accelerati on	Whether this service should, where possible, bypass data plane acceleration mechanisms.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

Property	Description
close_with_rst	Whether or not connections from clients should be closed with a RST packet, rather than a FIN packet. This avoids the TIME_WAIT state, which on rare occasions allows wandering duplicate packets to be safely ignored.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
completionrules	Rules that are run at the end of a transaction, in order, comma separated.
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
connect_timeout	The time, in seconds, for which an established connection can remain idle waiting for some initial data to be received from the client. The initial data is defined as a complete set of request headers for HTTP, SIP and RTSP services, or the first byte of data for all other services. A value of 0 will disable the timeout.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>
connection_errors_error_file	The error message to be sent to the client when the traffic manager detects an internal or backend error for the virtual server.
	<ul><li>Type: Reference(config-extra-file)</li><li>Required: false</li><li>Default value: "Default"</li></ul>
connection_keepalive	Whether or not the virtual server should use keepalive connections with the remote clients.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
connection_keepalive_timeout	The length of time that the virtual server should keep an idle keepalive connection before discarding it. A value of 0 (zero) will mean that the keepalives are never closed by the traffic manager.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10"</li></ul>
connection_max_client_buffer	The amount of memory, in bytes, that the virtual server should use to store data sent by the client. Larger values will use more memory, but will minimise the number of read() and write() system calls that the traffic manager must perform.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "65536"</li></ul>

Property	Description
connection_max_server_buffe r	The amount of memory, in bytes, that the virtual server should use to store data returned by the server. Larger values will use more memory, but will minimise the number of read() and write() system calls that the traffic manager must perform.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "65536"</li></ul>
connection_max_transaction_ duration	The total amount of time a transaction can take, counted from the first byte being received until the transaction is complete. For HTTP, this can mean all data has been written in both directions, or the connection has been closed; in most other cases it is the same as the connection being closed. The default value of 0 means there is no maximum duration, i.e., transactions can take arbitrarily long if none of the other timeouts occur.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
connection_server_first_banner	If specified, the traffic manager will use the value as the banner to send for server-first protocols such as FTP, POP, SMTP and IMAP. This allows rules to use the first part of the client data (such as the username) to select a pool. The banner should be in the correct format for the protocol, e.g. for FTP it should start with "220"
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
connection_timeout	A connection should be closed if no additional data has been received for this period of time. A value of 0 (zero) will disable this timeout.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "300"</li></ul>
cookie_domain	The way in which the traffic manager should rewrite the domain portion of any cookies set by a back-end web server.
	<ul> <li>Type: Enum(UInt)</li> <li>Required: false</li> <li>Default value: "no_rewrite"</li> <li>Permitted values:    "no_rewrite": Do not rewrite the domain</li> </ul>
	"set_to_named": Rewrite the domain to the named domain value
	"set_to_request": Rewrite the domain to the host header of the request
cookie_new_domain	<ul> <li>The domain to use when rewriting a cookie's domain to a named value.</li> <li>Type: String</li> <li>Required: false</li> <li>Default value: <none></none></li> </ul>

Property	Description
cookie_path_regex	If you wish to rewrite the path portion of any cookies set by a back-end web server, provide a regular expression to match the path:
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
cookie_path_replace	If cookie path regular expression matches, it will be replaced by this substitution. Parameters \$1-\$9 can be used to represent bracketed parts of the regular expression.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
cookie_secure	Whether or not the traffic manager should modify the "secure" tag of any cookies set by a back-end web server.
	<ul> <li>Type: Enum(UInt)</li> <li>Required: false</li> <li>Default value: "no_modify"</li> <li>Permitted values:     "no_modify": Do not modify the 'secure' tag</li> </ul>
	"set_secure": Set the 'secure' tag
dos ados client subnet	"unset_secure": Unset the 'secure' tag
dns_edns_client_subnet	<ul> <li>Enable/Disable use of EDNS client subnet option</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
dns_edns_udpsize	EDNS UDP size advertised in responses.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "4096"</li></ul>
dns_max_udpsize	Maximum UDP answer size.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "4096"</li></ul>
dns_rrset_order	Response record ordering.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "fixed"</li> <li>Permitted values:    "cyclic": Cyclic</li> <li>"fixed": Fixed</li> </ul>
dns_verbose	<ul> <li>Whether or not the DNS Server should emit verbose logging. This is useful for diagnosing problems.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>

Property	Description
dns_zones	The DNS zones  Type: Set(String) Required: false Default value: <none></none>
enabled	<ul> <li>Whether the virtual server is enabled.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
ftp_data_source_port	The source port to be used for active-mode FTP data connections. If 0, a random high port will be used, otherwise the specified port will be used. If a port below 1024 is required you must first explicitly permit use of low ports with the data_bind_low global setting.  Type: UInt Required: false Default value: <none></none>
ftp_force_client_secure	Whether or not the virtual server should require that incoming FTP data connections from the client originate from the same IP address as the corresponding client control connection.  Type: Boolean Required: false Default value: false
ftp_force_server_secure	<ul> <li>Whether or not the virtual server should require that incoming FTP data connections from the nodes originate from the same IP address as the node.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
ftp_port_range_high	If non-zero, then this controls the upper bound of the port range to use for FTP data connections.  Type: UInt Required: false Default value: <none></none>
ftp_port_range_low	If non-zero, then this controls the lower bound of the port range to use for FTP data connections.  Type: UInt Required: false Default value: <none></none>
ftp_ssl_data	Use SSL on the data connection as well as the control connection (if not enabled it is left to the client and server to negotiate this).  • Type: Boolean  • Required: false  • Default value: false

Property	Description
glb_services	The associated GLB services for this DNS virtual server.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
gzip_compress_level	Compression level (1-9, 1=low, 9=high).
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "1"</li></ul>
gzip_enabled	Compress web pages sent back by the server.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
gzip_etag_rewrite	How the ETag header should be manipulated when compressing content.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "wrap"</li> <li>Permitted values:    "delete": Delete the ETag header</li> </ul>
	"ignore": Leave the ETag unchanged
	"weaken": Change the ETag header to specify a weak match
	"wrap": Wrap the ETag, and attempt to unwrap safe conditional requests
gzip_include_mime	MIME types to compress. Complete MIME types can be used, or a type can end in a '*' to match multiple types.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: "text/html text/plain"</li></ul>
gzip_max_size	Maximum document size to compress (0 means unlimited).
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "10000000"</li></ul>
gzip_min_size	Minimum document size to compress.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "1000"</li></ul>
gzip_no_size	Compress documents with no given size.  Type: Boolean Required: false Default value: false

Property	Description
http2_connect_timeout	The time, in seconds, to wait for a request on a new HTTP/2 connection. If no request is received within this time, the connection will be closed. This setting overrides the connect_timeout setting. If set to 0 (zero), the value of connect_timeout will be used instead.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
http2_data_frame_size	This setting controls the preferred frame size used when sending body data to the client. If the client specifies a smaller maximum size than this setting, the client's maximum size will be used. Every data frame sent has at least a 9-byte header, in addition to this frame size, prepended to it.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "4096"</li></ul>
http2_enabled	This setting allows the HTTP/2 protocol to be used by a HTTP virtual server. Unless use of HTTP/2 is negotiated by the client, the virtual server will fall back to HTTP 1.x automatically.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
http2_header_table_size	This setting controls the amount of memory allowed for header compression on each HTTP/2 connection.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "4096"</li></ul>
http2_headers_index_blacklist	A list of header names that should never be compressed using indexing.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
http2_headers_index_default	The HTTP/2 HPACK compression scheme allows for HTTP headers to be compressed using indexing. Sensitive headers can be marked as "never index", which prevents them from being compressed using indexing. When this setting is Yes, only headers included in http2!headers_index_blacklist are marked as "never index". When this setting is No, all headers will be marked as "never index" unless they are included in http2!headers_index_whitelist.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
http2_headers_index_whitelist	A list of header names that can be compressed using indexing when the value of http2!headers_index_default is set to No.  Type: Set(String) Required: false Default value: <none></none>

Property	Description
http2_headers_size_limit	The maximum size, in bytes, of decompressed headers for an HTTP/2 request. If the limit is exceeded, the connection on which the request was sent will be dropped. A value of 0 disables the limit check. If a service protection class with http!max_header_length configured is associated with this service then that setting will take precedence.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "262144"</li></ul>
http2_idle_timeout_no_stream s	The time, in seconds, to wait for a new HTTP/2 request on a previously used HTTP/2 connection that has no open HTTP/2 streams. If an HTTP/2 request is not received within this time, the connection will be closed. A value of 0 (zero) will disable the timeout.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "120"</li></ul>
http2_idle_timeout_open_stre ams	The time, in seconds, to wait for data on an idle HTTP/2 connection, which has open streams, when no data has been sent recently (e.g. for long-polled requests). If data is not sent within this time, all open streams and the HTTP/2 connection will be closed. A value of 0 (zero) will disable the timeout.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "600"</li></ul>
http2_max_concurrent_strea ms	This setting controls the number of streams a client is permitted to open concurrently on a single connection.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "200"</li></ul>
http2_max_frame_size	This setting controls the maximum HTTP/2 frame size clients are permitted to send to the traffic manager.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "16384"</li></ul>
http2_max_header_padding	The maximum size, in bytes, of the random-length padding to add to HTTP/2 header frames. The padding, a random number of zero bytes up to the maximum specified.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
http2_merge_cookie_headers	Whether Cookie headers received from an HTTP/2 client should be merged into a single Cookie header using RFC6265 rules before forwarding to an HTTP/1.1 server. Some web applications do not handle multiple Cookie headers correctly.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

Property	Description
http2_stream_window_size	This setting controls the flow control window for each HTTP/2 stream. This will limit the memory used for buffering when the client is sending body data faster than the pool node is reading it.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "65535"</li></ul>
http_chunk_overhead_forward ing	Handling of HTTP chunk overhead. When vTM receives data from a server or client that consists purely of protocol overhead (contains no payload), forwarding of such segments is delayed until useful payload data arrives (setting "lazy"). Changing this key to "eager" will make vTM incur the overhead of immediately passing such data on; it should only be used with HTTP peers whose chunk handling requires it.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "lazy"</li> <li>Permitted values:     "eager": Forward all data, even when no new payload information is available.</li> </ul>
	"lazy": Only forward segments when useful payload data is available.
http_location_regex	If the 'Location' header matches this regular expression, rewrite the header using the 'location_replace' pattern.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
http_location_replace	If the 'Location' header matches the 'location_regex' regular expression, rewrite the header with this pattern (parameters such as \$1-\$9 can be used to match parts of the regular expression):
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
http_location_rewrite	The action the virtual server should take if the "Location" header does not match the location_regex regular expression.
	<ul> <li>Type: Enum(UInt)</li> <li>Required: false</li> <li>Default value: "if_host_matches"</li> <li>Permitted values:         <ul> <li>"always": Rewrite the hostname to the request's "Host" header, and rewrite the protocol and port if necessary;</li> </ul> </li> </ul>
	"if_host_matches": Do not rewrite the hostname. Rewrite the protocol and port if the hostname matches the request's "Host" header. "never": Nothing;

Property	Description
http_mime_default	Auto-correct MIME types if the server sends the "default" MIME type for files.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "text/plain"</li></ul>
http_mime_detect	Auto-detect MIME types if the server does not provide them.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
kerberos_protocol_transition_ enabled	Whether or not the virtual server should use Kerberos Protocol Transition.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
kerberos_protocol_transition_ principal	The Kerberos principal this virtual server should use to perform Kerberos Protocol Transition.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
kerberos_protocol_transition_t	The Kerberos principal name of the service this virtual server targets.
arget	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
l4accel_rst_on_service_failure	Whether the virtual server should send a TCP RST packet or ICMP error message if a service is unavailable, or if an established connection to a node fails.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
l4accel_service_ip_snat	Whether or not backend connections should be configured to use the ingress service IP as the source IP for the back-end connection when Source NAT is enabled for the pool used by the service. Requires I4accel!state_sync to be enabled.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
l4accel_state_sync	Whether the state of active connections will be synchronized across the cluster for L4Accel services, such that connections will persist in the event of a failover. Note that the service must listen only on Traffic IP groups for this setting to be enabled.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

Property	Description
l4accel_tcp_msl	The maximum segment lifetime, in seconds, of a TCP segment being handled by the traffic manager. This setting determines for how long information about a connection will be retained after receiving a two-way FIN or RST.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "8"</li></ul>
l4accel_timeout	The number of seconds after which a connection will be closed if no further packets have been received on it.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "1800"</li></ul>
l4accel_udp_count_requests	Whether a connection should be closed when the number of UDP response datagrams received from the server is equal to the number of request datagrams that have been sent by the client. If set to No the connection will be closed after the first response has been received from the server. This setting takes precedence over I4accelloptimized_aging setting.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
listen_on_any	Whether to listen on all IP addresses
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
listen_on_hosts	Hostnames and IP addresses to listen on
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
listen_on_traffic_ips	Traffic IP Groups to listen on
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
log_client_connection_failures	Should the virtual server log failures occurring on connections to clients.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
log_enabled	<ul> <li>Whether or not to log connections to the virtual server to a disk on the file system.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>

Property	Description
log_filename	The name of the file in which to store the request logs. The filename can contain macros which will be expanded by the traffic manager to generate the full filename.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: "%zeushome%/zxtm/log/%v.log"</li></ul>
log_format	The log file format. This specifies the line of text that will be written to the log file when a connection to the traffic manager is completed. Many parameters from the connection can be recorded using macros.
	<ul> <li>Type: String</li> <li>Required: false</li> <li>Default value: "%h %l %u %t "%r" %s %b "%{Referer}i" "%{Useragent}i""</li> </ul>
log_save_all	Whether to log all connections by default, or log no connections by default. Specific connections can be selected for addition to or exclusion from the log using the TrafficScript function requestlog.include().
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
log_server_connection_failure s	Should the virtual server log failures occurring on connections to nodes.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
log_session_persistence_verb	Should the virtual server log session persistence events.
ose	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
log_ssl_failures	Should the virtual server log failures occurring on SSL secure negotiation.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
max_concurrent_connections	The maximum number of concurrent TCP connections that will be handled by this virtual server. If set to a non-zero value, the traffic manager will limit the number of concurrent TCP connections that this virtual server will accept to the value specified. When the limit is reached, new connections to this virtual server will not be accepted. If set to 0 the number of concurrent TCP connections will not be limited.  Type: UInt Required: false Default value: <none></none>

Property	Description
note	A description for the virtual server.
	<ul><li>Type: FreeformString</li><li>Required: false</li><li>Default value: <none></none></li></ul>
pool	The default pool to use for traffic.
	<ul><li>Type: Reference(config-pool)</li><li>Required: true</li><li>Default value: <none></none></li></ul>
port	The port on which to listen for incoming connections.
	<ul><li>Type: UInt</li><li>Required: true</li><li>Default value: <none></none></li></ul>
protection_class	The service protection class that should be used to protect this server, if any.  Type: String Required: false Default value: <none></none>

Property	Description
protocol	The protocol that the virtual server is using.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "http"</li> <li>Permitted values:     "client_first": Generic client first</li> </ul>
	"dns": DNS (UDP)
	"dns_tcp": DNS (TCP)
	"ftp": FTP
	"http": HTTP
	"https": SSL (HTTPS)
	"imaps": SSL (IMAPS)
	"imapv2": IMAPv2
	"imapv3": IMAPv3
	"imapv4": IMAPv4
	"l4accel_dns": L4Accel DNS
	"l4accel_generic": L4Accel Generic
	"l4accel_stateless": L4Accel Stateless
	"l4accel_tcp": L4Accel TCP
	"l4accel_udp": L4Accel UDP
	"ldap": LDAP
	"ldaps": SSL (LDAPS)
	"pop3": POP3
	"pop3s": SSL (POP3S)
	"rtsp": RTSP
	"server_first": Generic server first
	"siptcp": SIP (TCP)
	"sipudp": SIP (UDP)
	"smtp": SMTP
	"ssl": SSL
	"stream": Generic streaming
	"telnet": Telnet
	"udp": UDP
	"udpstreaming": UDP - Streaming

Property	Description
proxy_protocol	Expect connections to the traffic manager to be prefixed with a PROXY protocol header. If enabled, the information contained in the PROXY header will be available in TrafficScript. Connections that are not prefixed with a valid PROXY protocol header will be discarded.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
recent_connections_enabled	Whether or not connections handled by this virtual server should be shown on the Activity > Connections page.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
recent_connections_save_all	Whether or not all connections handled by this virtual server should be shown on the Connections page. Individual connections can be selectively shown on the Connections page using the recentconns.include() TrafficScript function.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
request_rules	Rules to be applied to incoming requests, in order, comma separated.
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
request_tracing_enabled	Record a trace of major connection processing events for each request and response.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
request_tracing_trace_io	Include details of individual I/O events in request and response traces. Requires request tracing to be enabled.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
response_rules	Rules to be applied to responses, in order, comma separated.
	<ul><li>Type: List(Reference(config-trafficscript))</li><li>Required: false</li><li>Default value: <none></none></li></ul>
rtsp_streaming_port_range_high	If non-zero this controls the upper bound of the port range to use for streaming data connections.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
rtsp_streaming_port_range_lo w	If non-zero this controls the lower bound of the port range to use for streaming data connections.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: <none></none></li></ul>
rtsp_streaming_timeout	If non-zero data-streams associated with RTSP connections will timeout if no data is transmitted for this many seconds.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "30"</li></ul>
sip_dangerous_requests	The action to take when a SIP request with body data arrives that should be routed to an external IP.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "node"</li> <li>Permitted values:   "forbid": Send a 403 Forbidden response to the client</li> </ul>
	"forward": Forward the request to its target URI (dangerous)
	"node": Send the request to a back-end node
sip_follow_route	Should the virtual server follow routing information contained in SIP requests. If set to No requests will be routed to the chosen back-end node regardless of their URI or Route header.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
sip_max_connection_mem	SIP clients can have several pending requests at one time. To protect the traffic manager against DoS attacks, this setting limits the amount of memory each client can use. When the limit is reached new requests will be sent a 413 response. If the value is set to 0 (zero) the memory limit is disabled.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "65536"</li></ul>

Property	Description
sip_mode	<ul> <li>The mode that this SIP virtual server should operate in.</li> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "sip_gateway"</li> <li>Permitted values:     "full_gateway": All SIP requests and responses and all session data will pass through vTM. A port range to use for the session data and a timeout value for inactive data connections can be specified in the additional settings that are displayed when the Full Gateway mode is selected.</li> <li>"route": The first SIP request in a session will pass through vTM, along with its responses, but all future requests that are part of the</li> </ul>
	same session will go directly to the back-end node that was chosen by the traffic manager.  "sip_gateway": All SIP requests and responses will pass through the traffic manager.
sip_rewrite_uri	Replace the Request-URI of SIP requests with the address of the selected back-end node.  Type: Boolean Required: false Default value: false
sip_streaming_port_range_hig h	If non-zero this controls the upper bound of the port range to use for streaming data connections.  Type: UInt Required: false Default value: <none></none>
sip_streaming_port_range_low	If non-zero, then this controls the lower bound of the port range to use for streaming data connections.  Type: UInt Required: false Default value: <none></none>
sip_streaming_timeout	If non-zero a UDP stream will timeout when no data has been seen within this time.  Type: UInt Required: false Default value: "60"
sip_timeout_messages	When timing out a SIP transaction, send a 'timed out' response to the client and, in the case of an INVITE transaction, a CANCEL request to the server.  Type: Boolean Required: false Default value: false

Property	Description
sip_transaction_timeout	The virtual server should discard a SIP transaction when no further messages have been seen within this time.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "30"</li></ul>
slm_class	The service level monitoring class that this server should use, if any.
	<ul><li>Type: Reference(config-slm)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
smtp_expect_starttls	Whether or not the traffic manager should expect the connection to start off in plain text and then upgrade to SSL using STARTTLS when handling SMTP traffic.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
so_nagle	Whether or not Nagle's algorithm should be used for TCP connections.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_add_http_headers	Whether or not the virtual server should add HTTP headers to each request to show the SSL connection parameters.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_client_cert_cas	The certificate authorities that this virtual server should trust to validate client certificates. If no certificate authorities are selected, and client certificates are requested, then all client certificates will be accepted.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_client_cert_headers	What HTTP headers the virtual server should add to each request to show the data in the client certificate.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "none"</li> <li>Permitted values: "all": Certificate fields and certificate text</li> </ul>
	"none": No data
	"simple": Certificate fields
ssl_decrypt	<ul> <li>Whether or not the virtual server should decrypt incoming SSL traffic.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>

Property	Description
ssl_elliptic_curves	The SSL elliptic curve preference list for SSL connections to this virtual server using TLS version 1.0 or higher. Leaving this empty will make the virtual server use the globally configured curve preference list. The named curves P256, P384 and P521 may be configured.
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_honor_fallback_scsv	Whether or not the Fallback SCSV sent by TLS clients is honored by this virtual server. Choosing the global setting means the value of configuration key ssl!honor_fallback_scsv from the Global Settings section of the System tab will be enforced.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "use_default"</li> <li>Permitted values:    "disabled": Disable Fallback SCSV</li> </ul>
	"enabled": Enable Fallback SCSV "use_default": Use the global setting for Fallback SCSV
ssl_issued_certs_never_expire	When the virtual server verifies certificates signed by these certificate authorities, it doesn't check the 'not after' date, i.e., they are considered valid even after their expiration date has passed (but not if they have been revoked).  • Type: Set(String)
	<ul> <li>Required: false</li> <li>Default value: <none></none></li> </ul>
ssl_issued_certs_never_expire_depth	This setting gives the number of certificates in a certificate chain beyond those listed as issued_certs_never_expire whose certificate expiry will not be checked. For example "0" will result in the expiry checks being made for certificates issued by issued_certs_never_expire certificates, "1" will result in no expiry checks being performed for the certificates directly issued by issued_certs_never_expire certificates, "2" will avoid checking expiry for certificates issued by certificates issued by the issued_certs_never_expire certificates as well, and so on.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "1"</li></ul>
ssl_ocsp_enable	<ul> <li>Whether or not the traffic manager should use OCSP to check the revocation status of client certificates.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>

Property	Description
ssl_ocsp_issuers	A table of certificate issuer specific OCSP settings.  Type: Table Required: false Primary key: Issuer (String): The name of an issuer (or DEFAULT for default OCSP settings). (Required) Sub keys: Iaia (Boolean): Whether the traffic manager should use AIA information contained in a client certificate to determine which OCSP responder to contact. In once (Enum(String)): How to use the OCSP nonce extension, which protects against OCSP replay attacks. Some OCSP servers do not support nonces.  Permitted values: "off": No nonce check "on": Use nonce, server does not have to reply with nonce "strict": Use nonce, server must reply with nonce "strict": Use nonce, server must reply with nonce "required (Enum(String)): Whether we should do an OCSP check for this issuer, and whether it is required or optional.  Permitted values: "none": None "optional": OCSP check optional "strict": OCSP check required responder_cert (String): The expected responder certificate. signer (String): The certificate with which to sign the request, if any. url (String): Which OCSP responders this virtual server should use to verify client certificates.
ssl_ocsp_issuers_json	A Traffic Manager REST-compatible JSON representation of the "ssl_ocsp_issuers" table property. Use this field with the "vtm_virtual_server_ocsp_issuers_table" data source for dynamic table generation from input variables.  • Type: String • Required: false • Default value: <none></none>
ssl_ocsp_max_response_age	The number of seconds for which an OCSP response is considered valid if it has not yet exceeded the time specified in the 'nextUpdate' field. If set to 0 (zero) then OCSP responses are considered valid until the time specified in their 'nextUpdate' field.  Type: UInt Required: false Default value: <none></none>

Property	Description
ssl_ocsp_stapling	If OCSP URIs are present in certificates used by this virtual server, then enabling this option will allow the traffic manager to provide OCSP responses for these certificates as part of the handshake, if the client sends a TLS status_request extension in the ClientHello.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_ocsp_time_tolerance	The number of seconds outside the permitted range for which the 'thisUpdate' and 'nextUpdate' fields of an OCSP response are still considered valid.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "30"</li></ul>
ssl_ocsp_timeout	The number of seconds after which OCSP requests will be timed out.
	<ul><li>Type: Ulnt</li><li>Required: false</li><li>Default value: "10"</li></ul>
ssl_prefer_sslv3	Deprecated. Formerly allowed a preference for SSLv3 for performance reasons.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_request_client_cert	Whether or not the virtual server should request an identifying SSL certificate from each client.
	<ul> <li>Type: Enum(UInt)</li> <li>Required: false</li> <li>Default value: "dont_request"</li> <li>Permitted values:    "dont_request": Do not request a client certificate</li> </ul>
	"request": Request, but do not require a client certificate
	"require": Require a client certificate
ssl_send_close_alerts	Whether or not to send an SSL/TLS "close alert" when the traffic manager is initiating an SSL socket disconnection.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
ssl_server_cert_alt_certificates	The SSL certificates and corresponding private keys.
	<ul><li>Type: List(String)</li><li>Required: false</li><li>Default value: <none></none></li></ul>
ssl_server_cert_default	The default SSL certificate to use for this virtual server.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
ssl_server_cert_host_mapping	<ul> <li>Host specific SSL server certificate mappings.</li> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>host (String): Host which this entry refers to. (Required)</li> </ul> </li> <li>Sub keys: <ul> <li>certificate (String): The SSL server certificate for a particular destination site IP.</li> <li>alt_certificates (List(String)): The SSL server certificates for a particular destination site IP.</li> </ul> </li> </ul>
ssl_server_cert_host_mapping _json	A Traffic Manager REST-compatible JSON representation of the "ssl_server_cert_host_mapping" table property. Use this field with the "vtm_virtual_server_server_cert_host_mapping_table" data source for dynamic table generation from input variables.  • Type: String • Required: false • Default value: <none></none>
ssl_signature_algorithms	The SSL signature algorithms preference list for SSL connections to this virtual server using TLS version 1.2 or higher. Leaving this empty will make the virtual server use the globally configured preference list, signature_algorithms in the ssl section of the global_settings resource. See there and in the online help for how to specify SSL signature algorithms.  Type: String Required: false Default value: <none></none>
ssl_ssl_ciphers	The SSL/TLS ciphers to allow for connections to this virtual server. Leaving this empty will make the virtual server use the globally configured ciphers, see configuration key ssl!ssl3_ciphers in the Global Settings section of the System tab. See there for how to specify SSL/ TLS ciphers.  Type: String Required: false Default value: <none></none>
ssl_ssl_support_ssl2	No longer supported. Formerly controlled whether SSLv2 could be used for SSL connections to this virtual server.  Type: Enum(String) Required: false Default value: "use_default" Permitted values: "disabled": Disable SSLv2 "enabled": Enable SSLv2 (not recommended) "use_default": Use the global setting for SSLv2

Property	Description
ssl_ssl_support_ssl3	Whether or not SSLv3 is enabled for this virtual server. Choosing the global setting means the value of configuration key ssl!support_ssl3 from the Global Settings section of the System tab will be enforced.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "use_default"</li> <li>Permitted values: "disabled": Disable SSLv3</li> </ul>
	"enabled": Enable SSLv3
	"use_default": Use the global setting for SSLv3
ssl_ssl_support_tls1	Whether or not TLSv1.0 is enabled for this virtual server. Choosing the global setting means the value of configuration key ssl!support_tls1 from the Global Settings section of the System tab will be enforced.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "use_default"</li> <li>Permitted values: "disabled": Disable TLSv1.0</li> </ul>
	"enabled": Enable TLSv1.0
	"use_default": Use the global setting for TLSv1.0
ssl_ssl_support_tls1_1	Whether or not TLSv1.1 is enabled for this virtual server. Choosing the global setting means the value of configuration key ssl!support_tls1.1 from the Global Settings section of the System tab will be enforced.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "use_default"</li> <li>Permitted values: "disabled": Disable TLSv1.1</li> </ul>
	"enabled": Enable TLSv1.1
	"use_default": Use the global setting for TLSv1.1
ssl_ssl_support_tls1_2	Whether or not TLSv1.2 is enabled for this virtual server. Choosing the global setting means the value of configuration key ssl!support_tls1.2 from the Global Settings section of the System tab will be enforced.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "use_default"</li> <li>Permitted values:     "disabled": Disable TLSv1.2     "enabled": Enable TLSv1.2     "use_default": Use the global setting for TLSv1.2</li> </ul>

Property	Description
ssl_trust_magic	If the traffic manager is receiving traffic sent from another traffic manager, then enabling this option will allow it to decode extra information on the true origin of the SSL connection. This information is supplied by the first traffic manager.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
strip_x_forwarded_proto	Whether or not the virtual server should strip the 'X-Forwarded-Proto' header from incoming requests.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
syslog_enabled	Whether or not to log connections to the virtual server to a remote syslog host.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
syslog_format	The log format for the remote syslog. This specifies the line of text that will be sent to the remote syslog when a connection to the traffic manager is completed. Many parameters from the connection can be recorded using macros.
	<ul> <li>Type: String</li> <li>Required: false</li> <li>Default value: "%h %l %u %t "%r" %s %b "%{Referer}i" "%{Useragent}i""</li> </ul>
syslog_ip_end_point	The remote host and port (default is 514) to send request log lines to.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
syslog_msg_len_limit	Maximum length in bytes of a message sent to the remote syslog. Messages longer than this will be truncated before they are sent.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "1024"</li></ul>
tcp_proxy_close	If set to Yes the traffic manager will send the client FIN to the back-end server and wait for a server response instead of closing the connection immediately. This is only necessary for protocols that require half-close support to function correctly, such as "rsh". If the traffic manager is responding to the request itself, setting this key to Yes will cause the traffic manager to continue writing the response even after it has received a FIN from the client.  Type: Boolean Required: false Default value: false

Property	Description
transaction_export_brief	Whether to export a restricted set of metadata about transactions processed by this virtual server. If enabled, more verbose information such as client and server headers and request tracing events will be omitted from the exported data.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
transaction_export_enabled	Export metadata about transactions handled by this service to the globally configured endpoint. Data will be exported only if the global transaction_export!enabled setting is enabled.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
transaction_export_hi_res	Whether the transaction processing timeline included in the metadata export is recorded with a high, microsecond, resolution. If set to No, timestamps will be recorded with a resolution of milliseconds.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
transaction_export_http_head er_blacklist	The set of HTTP header names for which corresponding values should be redacted from the metadata exported by this virtual server.
	<ul><li>Type: Set(String)</li><li>Required: false</li><li>Default value: "Authorization"</li></ul>
transparent	Whether or not bound sockets should be configured for transparent proxying.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
udp_end_point_persistence	Whether UDP datagrams received from the same IP address and port are sent to the same pool node if they match an existing UDP session. Sessions are defined by the protocol being handled, for example SIP datagrams are grouped based on the value of the Call-ID header.  Type: Boolean Required: false Default value: false

Property	Description
udp_end_transaction	When the traffic manager should consider a UDP transaction to have ended.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "one_response"</li> <li>Permitted values:     "match_requests": When the number of responses matches the number of requests</li> </ul>
	"one_response": After one response
	"timeout": When they time out
udp_port_smp	Whether or not UDP datagrams should be distributed across all traffic manager processes. This setting is not recommended if the traffic manager will be handling connection-based UDP protocols.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
udp_response_datagrams_exp ected	The virtual server should discard any UDP connection and reclaim resources when the node has responded with this number of datagrams. For simple request/response protocols this can be often set to 1. If set to -1, the connection will not be discarded until the timeout is reached.
	<ul><li>Type: Int</li><li>Required: false</li><li>Default value: "1"</li></ul>
udp_timeout	The virtual server should discard any UDP connection and reclaim resources when no further UDP traffic has been seen within this time.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "7"</li></ul>
web_cache_control_out	The "Cache-Control" header to add to every cached HTTP response, no-cache or max-age=600 for example.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
web_cache_enabled	If set to Yes the traffic manager will attempt to cache web server responses.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>
web_cache_error_page_time	Time period to cache error pages for.  Type: UInt Required: false Default value: "30"

Property	Description
web_cache_max_time	Maximum time period to cache web pages for.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "600"</li></ul>
web_cache_refresh_time	If a cached page is about to expire within this time, the traffic manager will start to forward some new requests on to the web servers. A maximum of one request per second will be forwarded; the remainder will continue to be served from the cache. This prevents "bursts" of traffic to your web servers when an item expires from the cache. Setting this value to 0 will stop the traffic manager updating the cache before it expires.
	<ul><li>Type: UInt</li><li>Required: false</li><li>Default value: "2"</li></ul>

## vtm\_aptimizer\_profile

URI Endpoint: /api/tm/4.0/config/active/aptimizer/profiles

A Web Accelerator profile can be applied to an HTTP virtual server to enable automatic web content optimization.

```
# Example usage of vtm_aptimizer_profile resource...
resource "vtm_aptimizer_profile" "my_aptimizer_profile" {
   name = "MyAptimizerProfile"
}
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
background_after	If Web Accelerator can finish optimizing the resource within this time limit then serve the optimized content to the client, otherwise complete the optimization in the background and return the original content to the client. If set to 0, Web Accelerator will always wait for the optimization to complete before sending a response to the client.  Type: UInt Required: false Default value: <none></none>
background_on_additional_res ources	If a web page contains resources that have not yet been optimized, fetch and optimize those resources in the background and send a partially optimized web page to clients until all resources on that page are ready.  Type: Boolean Required: false
	Default value: false

Property	Description
mode	Set the Web Accelerator mode to turn acceleration on or off.
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "active"</li> <li>Permitted values:         <ul> <li>"active": On - Web Accelerator acceleration is enabled</li> </ul> </li> </ul>
	"idle": Off - Acceleration is disabled, but requests for Web Accelerator resources are served
	"stealth": Stealth - Acceleration is controlled by a cookie
show_info_bar	Show the Web Accelerator information bar on optimized web pages. This requires HTML optimization to be enabled in the acceleration settings.
	<ul><li>Type: Boolean</li><li>Required: false</li><li>Default value: false</li></ul>

### **Data Sources**

Data sources are used to obtain information about an object or environment.

#### Resources

Each configuration resource is also available as an identical Terraform "data source" object. All properties in a data source remain the same as the configuration resource on which it is based, but read-only. Configuration data sources allow a Terraform template to query the contents of a Traffic Manager configuration object that was created externally from the template. For example:

```
# Create a data source object to represent an existing virtual server
data "vtm_virtual_server" "my_vs_data" {
    name = "MyVS"
}

# Set up a new virtual server referencing the data source
resource "vtm_virtual_server" "my_new_vs" {
    name = "MyNewVS
    pool = "discard"
    port = 1234
    ssl_decrypt = true
    ssl_server_cert_default =
"${data.vtm_virtual_server.my_vs_data.ssl_server_cert_default}"
}
```

For details of the available properties for a particular resource, refer to the corresponding configuration resource reference earlier in this chapter.

#### **Resource Lists**

Resource list data sources represent a list of stored configuration objects of the named type. For example, to obtain the current list of virtual servers, use the "vtm\_virtual\_server\_list" data source. By default, a resource list data source returns all objects of the given type. To filter the results, use the "starts\_with", "ends\_with", "contains", or "regex\_match" filters in the data source definition. To obtain the resulting filtered object list, use the "object\_list" property.

```
# Create a list of all pools
data "vtm_pool_list" "my_pool_list" {}

# Create a list of virtual servers with names starting "Exchange_"
data "vtm_virtual_server_list" "my_vs_list" {
    starts_with = "Exchange_"
}

# Create a TrafficScript rule list based on a regex match
data "vtm_rule_list" "my_rule_list" {
    regex_match = "^Rule-.*?-[0-9]$"
}

# Use the rule list in a virtual server definition
resource "vtm_virtual_server" "my_vs" {
    ...
    request_rules = ["${data.vtm_rule_list.my_rule_list.object_list}"]
    ...
}
```

The available resource list data sources are:

- vtm\_action\_list
- vtm action program list
- vtm\_aptimizer\_profile\_list
- vtm\_aptimizer\_scope\_list
- vtm bandwidth list
- vtm\_bgpneighbor\_list
- vtm\_cloud\_api\_credential\_list
- vtm custom list
- vtm\_dns\_server\_zone\_file\_list
- vtm\_dns\_server\_zone\_list
- vtm\_event\_type\_list
- vtm\_extra\_file\_list
- vtm\_glb\_service\_list
- vtm\_kerberos\_keytab\_list
- vtm kerberos krb5conf list

- vtm\_kerberos\_principal\_list
- vtm\_license\_key\_list
- vtm\_location\_list
- vtm\_log\_export\_list
- vtm\_monitor\_list
- vtm\_monitor\_script\_list
- vtm\_persistence\_list
- vtm\_pool\_list
- vtm\_protection\_list
- vtm\_rate\_list
- vtm\_rule\_authenticator\_list
- vtm rule list
- vtm\_service\_level\_monitor\_list
- vtm\_ssl\_ca\_list
- vtm\_ssl\_client\_key\_list
- vtm\_ssl\_server\_key\_list
- vtm\_traffic\_ip\_group\_list
- vtm\_traffic\_manager\_list
- vtm\_user\_authenticator\_list
- vtm\_user\_group\_list
- vtm\_virtual\_server\_list

#### **Statistics**

Statistics data sources allow Terraform to access a Traffic Manager's SNMP counter values. Some statistics data sources access single objects and take no parameters (for example, vtm\_globals\_stats), while others represent a collection of objects and require a "name" parameter (for example, vtm\_virtual\_server\_stats):

```
# Single object
data "vtm_globals_stats" "global_stats" {}

# Collection of objects
data "vtm_virtual_server_stats" "vs_stats" {
    name = "MyVirtualServer"
}
```

#### vtm\_action\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/actions/\*

Actions statistics values.

```
# Example usage of vtm_action_stats data source...
data "vtm_action_stats" "my_action_stats" {
    name = "MyAction"
}

# Access with...
"${data.vtm action stats.my action stats.<FIELD NAME>}"
```

Field Name	Description
processed	Number of times this action has been processed.
	<ul><li>Type: UInt</li><li>SNMP name: "actionsProcessed"</li></ul>

#### vtm\_cache\_asp\_session\_cache\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/cache/asp\_session\_cache

Asp session cache statistics values.

```
# Example usage of vtm_cache_asp_session_cache_stats data source...
data "vtm_cache_asp_session_cache_stats" "my_cache_asp_session_cache_stats" {}

# Access with...
"${data.vtm cache asp session cache stats.my cache asp session cache stats.<FIELD NAME>}"
```

Field Name	Description
entries	The total number of ASP sessions stored in the cache.
	<ul><li>Type: Ulnt</li><li>SNMP name: "aspSessionCacheEntries"</li></ul>
entries_max	The maximum number of ASP sessions in the cache.
	<ul><li>Type: Ulnt</li><li>SNMP name: "aspSessionCacheEntriesMax"</li></ul>
hit_rate	The percentage of ASP session lookups that succeeded.
	<ul><li>Type: Ulnt</li><li>SNMP name: "aspSessionCacheHitRate"</li></ul>
hits	Number of times a ASP session entry has been successfully found in the cache.
	<ul><li>Type: Ulnt</li><li>SNMP name: "aspSessionCacheHits"</li></ul>
lookups	Number of times a ASP session entry has been looked up in the cache.
	<ul><li>Type: Ulnt</li><li>SNMP name: "aspSessionCacheLookups"</li></ul>

Field Name	Description
misses	Number of times a ASP session entry has not been available in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "aspSessionCacheMisses"</li></ul>
oldest	The age of the oldest ASP session in the cache (in seconds).
	<ul><li>Type: UInt</li><li>SNMP name: "aspSessionCacheOldest"</li></ul>

## vtm\_bandwidth\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/bandwidth/\*

Bandwidth statistics values.

```
# Example usage of vtm_bandwidth_stats data source...
data "vtm_bandwidth_stats" "my_bandwidth_stats" {
    name = "MyBandwidth"
}
# Access with...
"${data.vtm_bandwidth_stats.my_bandwidth_stats.<FIELD_NAME>}"
```

Field Name	Description
bytes_drop	Bytes dropped by this bandwidth class.
	<ul><li>Type: UInt64</li><li>SNMP name: "bandwidthClassBytesDrop"</li></ul>
bytes_drop_hi	Bytes dropped by this bandwidth class ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "bandwidthClassBytesDropHi"</li></ul>
bytes_drop_lo	Bytes dropped by this bandwidth class ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "bandwidthClassBytesDropLo"</li></ul>
bytes_out	Bytes output by connections assigned to this bandwidth class.
	<ul><li>Type: UInt64</li><li>SNMP name: "bandwidthClassBytesOut"</li></ul>
bytes_out_hi	Bytes output by connections assigned to this bandwidth class ( high 32bits ).
	Type: UInt SNMP name: "bandwidthClassBytesOutHi"
bytes_out_lo	Bytes output by connections assigned to this bandwidth class ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "bandwidthClassBytesOutLo"</li></ul>

Field Name	Description
guarantee	Guaranteed bandwidth class limit (kbits/s). Currently unused.
	<ul><li>Type: UInt</li><li>SNMP name: "bandwidthClassGuarantee"</li></ul>
maximum	Maximum bandwidth class limit (kbits/s).
	<ul><li>Type: UInt</li><li>SNMP name: "bandwidthClassMaximum"</li></ul>
pkts_drop	Number of packets dropped by this bandwidth class.
	<ul><li>Type: UInt64</li><li>SNMP name: "bandwidthClassPktsDrop"</li></ul>
pkts_drop_hi	Number of packets dropped by this bandwidth class ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "bandwidthClassPktsDropHi"</li></ul>
pkts_drop_lo	Number of packets dropped by this bandwidth class ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "bandwidthClassPktsDropLo"</li></ul>

## vtm\_cloud\_api\_credential\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/cloud\_api\_credentials/\*

Cloud api credentials statistics values.

```
# Example usage of vtm_cloud_api_credential_stats data source...
data "vtm_cloud_api_credential_stats" "my_cloud_api_credential_stats" {
    name = "MyCloudApiCredential"
}
# Access with...
"${data.vtm_cloud_api_credential_stats.my_cloud_api_credential_stats.<FIELD_NAME>}"
```

Field Name	Description
node_creations	The number of instance creation API requests made with this set of cloud credentials.
	<ul><li>Type: UInt</li><li>SNMP name: "cloudcredentialsNodeCreations"</li></ul>
node_deletions	The number of instance destruction API requests made with this set of cloud credentials.
	<ul><li>Type: UInt</li><li>SNMP name: "cloudcredentialsNodeDeletions"</li></ul>
status_requests	The number of status API requests made with this set of cloud credentials.
	<ul><li>Type: UInt</li><li>SNMP name: "cloudcredentialsStatusRequests"</li></ul>

### vtm\_connection\_rate\_limit\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/connection\_rate\_limit/\*

Connection rate limit statistics values.

```
# Example usage of vtm_connection_rate_limit_stats data source...
data "vtm_connection_rate_limit_stats" "my_connection_rate_limit_stats" {
    name = "MyConnectionRateLimit"
}

# Access with...
"${data.vtm_connection_rate_limit_stats.my_connection_rate_limit_stats.<FIELD_NAME>}"
```

Field Name	Description
conns_entered	Connections that have entered the rate class and have been queued.
	<ul><li>Type: UInt</li><li>SNMP name: "rateClassConnsEntered"</li></ul>
conns_left	Connections that have left the rate class.
	<ul><li>Type: UInt</li><li>SNMP name: "rateClassConnsLeft"</li></ul>
current_rate	The average rate that requests are passing through this rate class.
	<ul><li>Type: UInt</li><li>SNMP name: "rateClassCurrentRate"</li></ul>
dropped	Requests dropped from this rate class without being processed (e.g. timeouts).
	<ul><li>Type: UInt</li><li>SNMP name: "rateClassDropped"</li></ul>
max_rate_per_min	The maximum rate that requests may pass through this rate class (requests/min).
	<ul><li>Type: UInt</li><li>SNMP name: "rateClassMaxRatePerMin"</li></ul>
max_rate_per_sec	The maximum rate that requests may pass through this rate class (requests/sec).
	<ul><li>Type: UInt</li><li>SNMP name: "rateClassMaxRatePerSec"</li></ul>
queue_length	The current number of requests queued by this rate class.
	<ul><li>Type: UInt</li><li>SNMP name: "rateClassQueueLength"</li></ul>

#### vtm\_event\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/events/\*

Events statistics values.

```
# Example usage of vtm_event_stats data source...
data "vtm_event_stats" "my_event_stats" {
    name = "MyEvent"
}

# Access with...
"${data.vtm event stats.my event stats.<FIELD NAME>}"
```

Field Name	Description
matched	Number of times this event configuration has matched.
	<ul><li>Type: UInt</li><li>SNMP name: "eventsMatched"</li></ul>

#### vtm\_glb\_service\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/glb\_services/\*

Glb services statistics values.

```
# Example usage of vtm_glb_service_stats data source...
data "vtm_glb_service_stats" "my_glb_service_stats" {
    name = "MyGlbService"
}
# Access with...
"${data.vtm_glb_service_stats.my_glb_service_stats.<FIELD_NAME>}"
```

Field Name	Description
discarded	Number of A records this GLB Service has discarded.
	<ul><li>Type: UInt</li><li>SNMP name: "glbServiceDiscarded"</li></ul>
responses	Number of A records this GLB Service has altered.
	<ul><li>Type: UInt</li><li>SNMP name: "glbServiceResponses"</li></ul>
unmodified	Number of A records this GLB Service has passed through unmodified.
	<ul><li>Type: UInt</li><li>SNMP name: "glbServiceUnmodified"</li></ul>

#### vtm\_globals\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/globals

Globals statistics values.

```
# Example usage of vtm_globals_stats data source...
data "vtm_globals_stats" "my_globals_stats" {}
```

# Access with...

<sup>&</sup>quot;\${data.vtm\_globals\_stats.my\_globals\_stats.<FIELD\_NAME>}"

Field Name	Description
analytics_transactions_droppe d	Count of transaction metadata records that have been dropped  Type: UInt SNMP name: "analyticsTransactionsDropped"
analytics_transactions_export ed	Count of transaction metadata records that have been exported  Type: UInt SNMP name: "analyticsTransactionsExported"
analytics_transactions_memor y_usage	Number of bytes queued in the transaction export transmit buffers.  • Type: UInt • SNMP name: "analyticsTransactionsMemoryUsage"
data_entries	Number of entries in the TrafficScript data.get()/set() storage.  • Type: UInt • SNMP name: "dataEntries"
data_memory_usage	Number of bytes used in the TrafficScript data.get()/set() storage.  • Type: UInt • SNMP name: "dataMemoryUsage"
events_seen	Events seen by the traffic Manager's event handling process.  • Type: UInt  • SNMP name: "eventsSeen"
hourly_peak_bytes_in_per_sec ond	The peak bytes received from clients per second in the last hour.  Type: UInt SNMP name: "hourlyPeakBytesInPerSecond"
hourly_peak_bytes_out_per_se cond	The peak bytes sent to clients per second in the last hour.  Type: UInt SNMP name: "hourlyPeakBytesOutPerSecond"
hourly_peak_requests_per_sec ond	The peak requests per second in the last hour.  Type: UInt SNMP name: "hourlyPeakRequestsPerSecond"
hourly_peak_ssl_connections_ per_second	The peak ssl connections per second in the last hour.  Type: Ulnt SNMP name: "hourlyPeakSSLConnectionsPerSecond"
num_idle_connections	Total number of idle HTTP connections to all nodes (used for future HTTP requests).  Type: Ulnt SNMP name: "numIdleConnections"

Field Name	Description
number_child_processes	The number of traffic manager child processes.
	<ul><li>Type: UInt</li><li>SNMP name: "numberChildProcesses"</li></ul>
number_dnsa_cache_hits	Requests for DNS A records resolved from the traffic manager's local cache.
	<ul><li>Type: UInt</li><li>SNMP name: "numberDNSACacheHits"</li></ul>
number_dnsa_requests	Requests for DNS A records (hostname->IP address) made by the traffic manager.
	<ul><li>Type: UInt</li><li>SNMP name: "numberDNSARequests"</li></ul>
number_dnsptr_cache_hits	Requests for DNS PTR records resolved from the traffic manager's local cache.
	<ul><li>Type: UInt</li><li>SNMP name: "numberDNSPTRCacheHits"</li></ul>
number_dnsptr_requests	Requests for DNS PTR records (IP address->hostname) made by the traffic manager.
	<ul><li>Type: UInt</li><li>SNMP name: "numberDNSPTRRequests"</li></ul>
number_snmp_bad_requests	Malformed SNMP requests received.
	<ul><li>Type: UInt</li><li>SNMP name: "numberSNMPBadRequests"</li></ul>
number_snmp_get_bulk_requ	SNMP GetBulkRequests received.
ests	<ul><li>Type: UInt</li><li>SNMP name: "numberSNMPGetBulkRequests"</li></ul>
number_snmp_get_next_requ	SNMP GetNextRequests received.
ests	<ul><li>Type: UInt</li><li>SNMP name: "numberSNMPGetNextRequests"</li></ul>
number_snmp_get_requests	SNMP GetRequests received.
	<ul><li>Type: UInt</li><li>SNMP name: "numberSNMPGetRequests"</li></ul>
number_snmp_unauthorised_	SNMP requests dropped due to access restrictions.
requests	<ul><li>Type: UInt</li><li>SNMP name: "numberSNMPUnauthorisedRequests"</li></ul>
ssl_cipher_3des_decrypts	Bytes decrypted with 3DES.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipher3DESDecrypts"</li></ul>
ssl_cipher_3des_encrypts	Bytes encrypted with 3DES.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipher3DESEncrypts"</li></ul>

Field Name	Description
ssl_cipher_aes_decrypts	Bytes decrypted with AES.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherAESDecrypts"</li></ul>
ssl_cipher_aes_encrypts	Bytes encrypted with AES.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherAESEncrypts"</li></ul>
ssl_cipher_aes_gcm_decrypts	Bytes decrypted with AES-GCM.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherAESGCMDecrypts"</li></ul>
ssl_cipher_aes_gcm_encrypts	Bytes encrypted with AES-GCM.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherAESGCMEncrypts"</li></ul>
ssl_cipher_decrypts	Bytes decrypted with a symmetric cipher.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherDecrypts"</li></ul>
ssl_cipher_des_decrypts	Bytes decrypted with DES.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherDESDecrypts"</li></ul>
ssl_cipher_des_encrypts	Bytes encrypted with DES.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherDESEncrypts"</li></ul>
ssl_cipher_dh_agreements	Number of Diffie Hellman key agreements.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherDHAgreements"</li></ul>
ssl_cipher_dh_generates	Number of Diffie Hellman keys generated.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherDHGenerates"</li></ul>
ssl_cipher_dsa_signs	Number of DSA signing operations.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherDSASigns"</li></ul>
ssl_cipher_dsa_verifies	Number of DSA verifications.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherDSAVerifies"</li></ul>
ssl_cipher_ecdh_agreements	Number of Elliptic Curve Diffie Hellman key agreements.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherECDHAgreements"</li></ul>
ssl_cipher_ecdh_generates	Number of Elliptic Curve Diffie Hellman keys generated.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherECDHGenerates"</li></ul>

Field Name	Description
ssl_cipher_ecdsa_signs	Number of ECDSA signing operations.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherECDSASigns"</li></ul>
ssl_cipher_ecdsa_verifies	Number of ECDSA verifications.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherECDSAVerifies"</li></ul>
ssl_cipher_encrypts	Bytes encrypted with a symmetric cipher.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherEncrypts"</li></ul>
ssl_cipher_rc4_decrypts	Bytes decrypted with RC4.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherRC4Decrypts"</li></ul>
ssl_cipher_rc4_encrypts	Bytes encrypted with RC4.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherRC4Encrypts"</li></ul>
ssl_cipher_rsa_decrypts	Number of RSA decrypts.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherRSADecrypts"</li></ul>
ssl_cipher_rsa_decrypts_exter	Number of external RSA decrypts.
nal	<ul><li>Type: Ulnt</li><li>SNMP name: "sslCipherRSADecryptsExternal"</li></ul>
ssl_cipher_rsa_encrypts	Number of RSA encrypts.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherRSAEncrypts"</li></ul>
ssl_cipher_rsa_encrypts_exter	Number of external RSA encrypts.
nal	<ul><li>Type: UInt</li><li>SNMP name: "sslCipherRSAEncryptsExternal"</li></ul>
ssl_client_cert_expired	Number of times a client certificate has expired.
	<ul><li>Type: UInt</li><li>SNMP name: "sslClientCertExpired"</li></ul>
ssl_client_cert_invalid	Number of times a client certificate was invalid.
	<ul><li>Type: UInt</li><li>SNMP name: "sslClientCertInvalid"</li></ul>
ssl_client_cert_not_sent	Number of times a client certificate was required but not supplied.
	<ul><li>Type: UInt</li><li>SNMP name: "sslClientCertNotSent"</li></ul>
ssl_client_cert_revoked	Number of times a client certificate was revoked.
	Type: UInt     SNMP name: "sslClientCertRevoked"

Field Name	Description
ssl_connections	Number of SSL connections negotiated.
	<ul><li>Type: UInt</li><li>SNMP name: "sslConnections"</li></ul>
ssl_handshake_sslv2	Formerly provided the number of SSLv2 handshakes, now deprecated.
	<ul><li>Type: UInt</li><li>SNMP name: "sslHandshakeSSLv2"</li></ul>
ssl_handshake_sslv3	Number of SSLv3 handshakes.
	<ul><li>Type: Ulnt</li><li>SNMP name: "sslHandshakeSSLv3"</li></ul>
ssl_handshake_t_l_sv1	Number of TLSv1.0 handshakes.
	<ul><li>Type: Ulnt</li><li>SNMP name: "sslHandshakeTLSv1"</li></ul>
ssl_handshake_t_l_sv11	Number of TLSv1.1 handshakes.
	<ul><li>Type: Ulnt</li><li>SNMP name: "sslHandshakeTLSv11"</li></ul>
ssl_handshake_t_l_sv12	Number of TLSv1.2 handshakes.
	<ul><li>Type: Ulnt</li><li>SNMP name: "sslHandshakeTLSv12"</li></ul>
ssl_session_id_disk_cache_hit	Number of times the SSL session id was found in the disk cache and reused (deprecated, will always return 0).
	<ul><li>Type: Ulnt</li><li>SNMP name: "sslSessionIDDiskCacheHit"</li></ul>
ssl_session_id_disk_cache_mis s	Number of times the SSL session id was not found in the disk cache (deprecated, will always return 0).
	<ul><li>Type: Ulnt</li><li>SNMP name: "sslSessionIDDiskCacheMiss"</li></ul>
ssl_session_id_mem_cache_hit	Number of times the SSL session id was found in the cache and reused.
	<ul><li>Type: UInt</li><li>SNMP name: "sslSessionIDMemCacheHit"</li></ul>
ssl_session_id_mem_cache_mi	Number of times the SSL session id was not found in the cache.
SS	<ul><li>Type: UInt</li><li>SNMP name: "sslSessionIDMemCacheMiss"</li></ul>
sys_cpu_busy_percent	Percentage of time that the CPUs are busy.
	<ul><li>Type: UInt</li><li>SNMP name: "sysCPUBusyPercent"</li></ul>
sys_cpu_idle_percent	Percentage of time that the CPUs are idle.
	<ul><li>Type: Ulnt</li><li>SNMP name: "sysCPUldlePercent"</li></ul>

Field Name	Description
sys_cpu_system_busy_percent	Percentage of time that the CPUs are busy running system code.  • Type: UInt
	SNMP name: "sysCPUSystemBusyPercent"
sys_cpu_user_busy_percent	Percentage of time that the CPUs are busy running user-space code.
	<ul><li>Type: UInt</li><li>SNMP name: "sysCPUUserBusyPercent"</li></ul>
sys_fds_free	Number of free file descriptors.
	<ul><li>Type: UInt</li><li>SNMP name: "sysFDsFree"</li></ul>
sys_mem_buffered	Buffer memory (MBytes).
	<ul><li>Type: UInt</li><li>SNMP name: "sysMemBuffered"</li></ul>
sys_mem_free	Free memory (MBytes).
	<ul><li>Type: UInt</li><li>SNMP name: "sysMemFree"</li></ul>
sys_mem_in_use	Memory used (MBytes).
	<ul><li>Type: UInt</li><li>SNMP name: "sysMemInUse"</li></ul>
sys_mem_swap_total	Total swap space (MBytes).
	<ul><li>Type: UInt</li><li>SNMP name: "sysMemSwapTotal"</li></ul>
sys_mem_swapped	Amount of swap space in use (MBytes).
	<ul><li>Type: UInt</li><li>SNMP name: "sysMemSwapped"</li></ul>
sys_mem_total	Total memory (MBytes).
	<ul><li>Type: UInt</li><li>SNMP name: "sysMemTotal"</li></ul>
time_last_config_update	The time (in hundredths of a second) since the configuration of traffic manager was updated (this value will wrap if no configuration changes are made for 497 days).
	<ul><li>Type: UInt</li><li>SNMP name: "timeLastConfigUpdate"</li></ul>
total_backend_server_errors	Total errors returned from the backend servers.
	Type: UInt     SNMP name: "totalBackendServerErrors"
total_bad_dns_packets	Total number of malformed DNS response packets encountered from the backend servers.
	<ul><li>Type: UInt</li><li>SNMP name: "totalBadDNSPackets"</li></ul>

Field Name	Description
total_bytes_in	Bytes received by the traffic manager from clients.
	<ul><li>Type: UInt64</li><li>SNMP name: "totalBytesIn"</li></ul>
total_bytes_in_hi	Bytes received by the traffic manager from clients ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "totalBytesInHi"</li></ul>
total_bytes_in_lo	Bytes received by the traffic manager from clients ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "totalBytesInLo"</li></ul>
total_bytes_out	Bytes sent by the traffic manager to clients.
	<ul><li>Type: UInt64</li><li>SNMP name: "totalBytesOut"</li></ul>
total_bytes_out_hi	Bytes sent by the traffic manager to clients ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "totalBytesOutHi"</li></ul>
total_bytes_out_lo	Bytes sent by the traffic manager to clients ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "totalBytesOutLo"</li></ul>
total_conn	Total number of TCP connections received.
	<ul><li>Type: UInt</li><li>SNMP name: "totalConn"</li></ul>
total_current_conn	Number of TCP connections currently established.
	<ul><li>Type: UInt</li><li>SNMP name: "totalCurrentConn"</li></ul>
total_dns_responses	Total number of DNS response packets handled.
	<ul><li>Type: UInt</li><li>SNMP name: "totalDNSResponses"</li></ul>
total_requests	Total number of TCP requests received.
	<ul><li>Type: UInt</li><li>SNMP name: "totalRequests"</li></ul>
total_transactions	Total number of TCP requests being processed, after applying TPS limits.
	<ul><li>Type: UInt</li><li>SNMP name: "totalTransactions"</li></ul>
up_time	The time (in hundredths of a second) that vTM software has been operational for (this value will wrap if it has been running for more than 497 days).
	<ul><li>Type: UInt</li><li>SNMP name: "upTime"</li></ul>

## vtm\_traffic\_ips\_ip\_gateway\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/traffic\_ips/ip\_gateway

Ip gateway statistics values.

```
# Example usage of vtm_traffic_ips_ip_gateway_stats data source...
data "vtm_traffic_ips_ip_gateway_stats" "my_traffic_ips_ip_gateway_stats" {}

# Access with...
"${data.vtm_traffic_ips_ip_gateway_stats.my_traffic_ips_ip_gateway_stats.<FIELD_NAME>}"
```

Field Name	Description
arp_message	Number of ARP messages sent for raised Traffic IP Addresses.
	<ul><li>Type: UInt</li><li>SNMP name: "trafficIPARPMessage"</li></ul>
gateway_ping_requests	Number of ping requests sent to the gateway machine.
	<ul><li>Type: UInt</li><li>SNMP name: "trafficIPGatewayPingRequests"</li></ul>
gateway_ping_responses	Number of ping responses received from the gateway machine.
	<ul><li>Type: UInt</li><li>SNMP name: "trafficIPGatewayPingResponses"</li></ul>
node_ping_requests	Number of ping requests sent to the backend nodes.
	<ul><li>Type: UInt</li><li>SNMP name: "trafficIPNodePingRequests"</li></ul>
node_ping_responses	Number of ping responses received from the backend nodes.
	<ul><li>Type: UInt</li><li>SNMP name: "trafficIPNodePingResponses"</li></ul>
number	The number of traffic IPv4 addresses on this system.
	<ul><li>Type: UInt</li><li>SNMP name: "trafficIPNumber"</li></ul>
number_inet46	The number of traffic IP addresses on this system (includes IPv4 and IPv6 addresses).
	<ul><li>Type: UInt</li><li>SNMP name: "trafficIPNumberInet46"</li></ul>
number_raised	The number of traffic IPv4 addresses currently raised on this system.
	<ul><li>Type: UInt</li><li>SNMP name: "trafficIPNumberRaised"</li></ul>

Field Name	Description
number_raised_inet46	The number of traffic IP addresses currently raised on this system (includes IPv4 and IPv6 addresses).
	<ul><li>Type: UInt</li><li>SNMP name: "trafficIPNumberRaisedInet46"</li></ul>
ping_response_errors	Number of ping response errors.
	<ul><li>Type: UInt</li><li>SNMP name: "trafficIPPingResponseErrors"</li></ul>

## vtm\_cache\_ip\_session\_cache\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/cache/ip\_session\_cache

Ip session cache statistics values.

```
# Example usage of vtm_cache_ip_session_cache_stats data source...
data "vtm_cache_ip_session_cache_stats" "my_cache_ip_session_cache_stats" {}
# Access with...
```

"\${data.vtm\_cache\_ip\_session\_cache\_stats.my\_cache\_ip\_session\_cache\_stats.<FIELD\_NAME>}"

Field Name	Description
entries	The total number of IP sessions stored in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "ipSessionCacheEntries"</li></ul>
entries_max	The maximum number of IP sessions in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "ipSessionCacheEntriesMax"</li></ul>
hit_rate	The percentage of IP session lookups that succeeded.
	<ul><li>Type: UInt</li><li>SNMP name: "ipSessionCacheHitRate"</li></ul>
hits	Number of times a IP session entry has been successfully found in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "ipSessionCacheHits"</li></ul>
lookups	Number of times a IP session entry has been looked up in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "ipSessionCacheLookups"</li></ul>

Field Name	Description
misses	Number of times a IP session entry has not been available in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "ipSessionCacheMisses"</li></ul>
oldest	The age of the oldest IP session in the cache (in seconds).
	<ul><li>Type: Ulnt</li><li>SNMP name: "ipSessionCacheOldest"</li></ul>

### vtm\_cache\_j2ee\_session\_cache\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/cache/j2ee\_session\_cache

J2ee session cache statistics values.

```
# Example usage of vtm_cache_j2ee_session_cache_stats data source...
data "vtm_cache_j2ee_session_cache_stats" "my_cache_j2ee_session_cache_stats" {}

# Access with...
"${data.vtm_cache_j2ee_session_cache_stats.my_cache_j2ee_session_cache_stats.<FIELD_NAME>}
"
```

Field Name	Description
entries	The total number of J2EE sessions stored in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "j2eeSessionCacheEntries"</li></ul>
entries_max	The maximum number of J2EE sessions in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "j2eeSessionCacheEntriesMax"</li></ul>
hit_rate	The percentage of J2EE session lookups that succeeded.
	<ul><li>Type: UInt</li><li>SNMP name: "j2eeSessionCacheHitRate"</li></ul>
hits	Number of times a J2EE session entry has been successfully found in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "j2eeSessionCacheHits"</li></ul>
lookups	Number of times a J2EE session entry has been looked up in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "j2eeSessionCacheLookups"</li></ul>

Field Name	Description
misses	Number of times a J2EE session entry has not been available in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "j2eeSessionCacheMisses"</li></ul>
oldest	The age of the oldest J2EE session in the cache (in seconds).
	<ul><li>Type: UInt</li><li>SNMP name: "j2eeSessionCacheOldest"</li></ul>

## vtm\_listen\_ip\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/listen\_ips/\*

Listen ips statistics values.

```
# Example usage of vtm_listen_ip_stats data source...
data "vtm_listen_ip_stats" "my_listen_ip_stats" {
    name = "MyListenIp"
}
# Access with...
"${data.vtm_listen_ip_stats.my_listen_ip_stats.<FIELD_NAME>}"
```

Field Name	Description
bytes_in	Bytes sent to this listening IP.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "listenIPBytesIn"</li></ul>
bytes_in_hi	Bytes sent to this listening IP ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "listenIPBytesInHi"</li></ul>
bytes_in_lo	Bytes sent to this listening IP ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "listenIPBytesInLo"</li></ul>
bytes_out	Bytes sent from this listening IP.
	<ul><li>Type: UInt64</li><li>SNMP name: "listenIPBytesOut"</li></ul>
bytes_out_hi	Bytes sent from this listening IP ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "listenIPBytesOutHi"</li></ul>
bytes_out_lo	Bytes sent from this listening IP ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "listenIPBytesOutLo"</li></ul>

Field Name	Description
current_conn	TCP connections currently established to this listening IP.
	Type: UInt     SNMP name: "listenIPCurrentConn"
max_conn	Maximum number of simultaneous TCP connections this listening IP has processed at any one time.
	<ul><li>Type: Ulnt</li><li>SNMP name: "listenIPMaxConn"</li></ul>
total_conn	Formerly provided the number of requests sent to this listening IP, now deprecated.
	<ul><li>Type: UInt</li><li>SNMP name: "listenIPTotalConn"</li></ul>
total_requests	Requests sent to this listening IP.
	<ul><li>Type: UInt64</li><li>SNMP name: "listenIPTotalRequests"</li></ul>
total_requests_hi	Requests sent to this listening IP.
	<ul><li>Type: UInt</li><li>SNMP name: "listenIPTotalRequestsHi"</li></ul>
total_requests_lo	Requests sent to this listening IP.
	<ul><li>Type: UInt</li><li>SNMP name: "listenIPTotalRequestsLo"</li></ul>

# vtm\_location\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/locations/\*

Locations statistics values.

```
# Example usage of vtm_location_stats data source...
data "vtm_location_stats" "my_location_stats" {
    name = "MyLocation"
}

# Access with...
"${data.vtm location stats.my location stats.<FIELD NAME>}"
```

Field Name	Description
load	The mean load metric for this location.
	<ul><li>Type: UInt</li><li>SNMP name: "locationLoad"</li></ul>
responses	Number of A records that have been altered to point to this location.
	<ul><li>Type: UInt</li><li>SNMP name: "locationResponses"</li></ul>

### vtm\_network\_interface\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/network\_interface/\*

Network interface statistics values.

```
# Example usage of vtm_network_interface_stats data source...
data "vtm_network_interface_stats" "my_network_interface_stats" {
    name = "MyNetworkInterface"
}

# Access with...
"${data.vtm_network_interface_stats.my_network_interface_stats.<FIELD_NAME>}"
```

Field Name	Description
collisions	The number of collisions reported by this interface.
	<ul><li>Type: UInt</li><li>SNMP name: "interfaceCollisions"</li></ul>
rx_bytes	Bytes received by this interface.
	<ul><li>Type: UInt64</li><li>SNMP name: "interfaceRxBytes"</li></ul>
rx_bytes_hi	Bytes received by this interface ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "interfaceRxBytesHi"</li></ul>
rx_bytes_lo	Bytes received by this interface ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "interfaceRxBytesLo"</li></ul>
rx_errors	The number of receive errors reported by this interface.
	<ul><li>Type: UInt</li><li>SNMP name: "interfaceRxErrors"</li></ul>
rx_packets	The number of packets received by this interface.
	<ul><li>Type: UInt</li><li>SNMP name: "interfaceRxPackets"</li></ul>
tx_bytes	Bytes transmitted by this interface.
	<ul><li>Type: UInt64</li><li>SNMP name: "interfaceTxBytes"</li></ul>
tx_bytes_hi	Bytes transmitted by this interface ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "interfaceTxBytesHi"</li></ul>
tx_bytes_lo	Bytes transmitted by this interface ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "interfaceTxBytesLo"</li></ul>

Field Name	Description
tx_errors	The number of transmit errors reported by this interface.
	<ul><li>Type: UInt</li><li>SNMP name: "interfaceTxErrors"</li></ul>
tx_packets	The number of packets transmitted by this interface.
	<ul><li>Type: UInt</li><li>SNMP name: "interfaceTxPackets"</li></ul>

### vtm\_nodes\_node\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/nodes/node/\*

Node statistics values.

```
# Example usage of vtm_nodes_node_stats data source...
data "vtm_nodes_node_stats" "my_nodes_node_stats" {
    name = "MyNodesNode"
}
# Access with...
"${data.vtm_nodes_node_stats.my_nodes_node_stats.<FIELD_NAME>}"
```

Field Name	Description
bytes_from_node_hi	Bytes received from this node ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "nodeBytesFromNodeHi"</li></ul>
bytes_from_node_lo	Bytes received from this node ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "nodeBytesFromNodeLo"</li></ul>
bytes_to_node_hi	Bytes sent to this node ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "nodeBytesToNodeHi"</li></ul>
bytes_to_node_lo	Bytes sent to this node ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "nodeBytesToNodeLo"</li></ul>
current_conn	Requests currently established to this node. ( does not include idle keepalives ).
	<ul><li>Type: UInt</li><li>SNMP name: "nodeCurrentConn"</li></ul>
current_requests	Connections currently established to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeCurrentRequests"</li></ul>

Field Name	Description
errors	Number of timeouts, connection problems and other errors for this node.  • Type: UInt
	SNMP name: "nodeErrors"
failures	Failures of this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeFailures"</li></ul>
new_conn	Requests that created a new connection to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeNewConn"</li></ul>
pooled_conn	Requests that reused an existing pooled/keepalive connection rather than creating a new TCP connection.
	<ul><li>Type: UInt</li><li>SNMP name: "nodePooledConn"</li></ul>
port	The port this node listens on.
	<ul><li>Type: UInt</li><li>SNMP name: "nodePort"</li></ul>
response_max	Maximum response time (ms) in the last second for this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeResponseMax"</li></ul>
response_mean	Mean response time (ms) in the last second for this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeResponseMean"</li></ul>
response_min	Minimum response time (ms) in the last second for this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeResponseMin"</li></ul>
state	The state of this node.
	<ul><li>Type: Enum(String)</li><li>SNMP name: "nodeState"</li><li>Permitted values: "alive": alive(1)</li></ul>
	"dead": dead(2)
	"unknown": unknown(3)
total_conn	Requests sent to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeTotalConn"</li></ul>

# vtm\_nodes\_node\_inet46\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/nodes/node\_inet46/\*

Node inet46 statistics values.

```
# Example usage of vtm_nodes_node_inet46_stats data source...
data "vtm_nodes_node_inet46_stats" "my_nodes_node_inet46_stats" {
    name = "MyNodesNodeInet46"
}

# Access with...
"${data.vtm nodes node inet46 stats.my nodes node inet46 stats.<FIELD NAME>}"
```

Field Name	Description
bytes_from_node	Bytes received from this node.
	<ul><li>Type: UInt64</li><li>SNMP name: "nodeInet46BytesFromNode"</li></ul>
bytes_from_node_hi	Bytes received from this node ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46BytesFromNodeHi"</li></ul>
bytes_from_node_lo	Bytes received from this node ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46BytesFromNodeLo"</li></ul>
bytes_to_node	Bytes sent to this node.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "nodelnet46BytesToNode"</li></ul>
bytes_to_node_hi	Bytes sent to this node ( high 32bits ).
	<ul><li>Type: Ulnt</li><li>SNMP name: "nodelnet46BytesToNodeHi"</li></ul>
bytes_to_node_lo	Bytes sent to this node ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46BytesToNodeLo"</li></ul>
current_conn	Current connections established to this node, includes idle connections.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46CurrentConn"</li></ul>
current_requests	Active connections established to this node, does not include idle connections.
	<ul><li>Type: UInt</li><li>SNMP name: "nodelnet46CurrentRequests"</li></ul>
errors	Number of timeouts, connection problems and other errors for this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46Errors"</li></ul>
failures	Failures of this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46Failures"</li></ul>

Field Name	Description
idle_conns	Number of idle HTTP connections to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46IdleConns"</li></ul>
new_conn	Requests that created a new connection to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46NewConn"</li></ul>
pooled_conn	Requests that reused an existing pooled/keepalive connection rather than creating a new TCP connection.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46PooledConn"</li></ul>
port	The port this node listens on.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46Port"</li></ul>
response_max	Maximum response time (ms) in the last second for this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46ResponseMax"</li></ul>
response_mean	Mean response time (ms) in the last second for this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46ResponseMean"</li></ul>
response_min	Minimum response time (ms) in the last second for this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46ResponseMin"</li></ul>
state	The state of this node.
	<ul> <li>Type: Enum(String)</li> <li>SNMP name: "nodeInet46State"</li> <li>Permitted values:     "alive": alive(1)</li> </ul>
	"dead": dead(2)
	"unknown": unknown(3)
total_conn	Requests sent to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "nodeInet46TotalConn"</li></ul>

# $vtm\_per\_location\_service\_stats$

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/per\_location\_service/\*

Per location service statistics values.

```
# Example usage of vtm_per_location_service_stats data source...
data "vtm_per_location_service_stats" "my_per_location_service_stats" {
    name = "MyPerLocationService"
}

# Access with...
"${data.vtm per location service stats.my per location service stats.<FIELD NAME>}"
```

LB Service. ng" GLB Service.
GLB Service.
GLB Service.
endState"
3 Service.
LB Service.
orState"
d to point to this location
onses"
e.

## vtm\_per\_node\_slm\_per\_node\_service\_level\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/per\_node\_slm/per\_node\_service\_level/\*

Per node service level statistics values.

```
# Example usage of vtm_per_node_slm_per_node_service_level_stats data source...
data "vtm_per_node_slm_per_node_service_level_stats"
"my_per_node_slm_per_node_service_level_stats" {
    name = "MyPerNodeSlmPerNodeServiceLevel"
}

# Access with...
"${data.vtm_per_node_slm_per_node_service_level_stats.my_per_node_slm_per_node_service_level_stats.
```

Field Name	Description
node_port	The port number of this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perNodeServiceLevelNodePort"</li></ul>
response_max	Maximum response time (ms) in the last second for this SLM class to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perNodeServiceLevelResponseMax"</li></ul>
response_mean	Mean response time (ms) in the last second for this SLM class to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perNodeServiceLevelResponseMean"</li></ul>
response_min	Minimum response time (ms) in the last second for this SLM class to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perNodeServiceLevelResponseMin"</li></ul>
total_conn	Requests handled by this SLM class to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perNodeServiceLevelTotalConn"</li></ul>
total_non_conf	Non-conforming requests handled by this SLM class to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perNodeServiceLevelTotalNonConf"</li></ul>

# vtm\_per\_node\_slm\_per\_node\_service\_level\_inet46\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/per\_node\_slm/per\_node\_service\_level\_inet46/\*

Per node service level inet46 statistics values.

```
# Example usage of vtm_per_node_slm_per_node_service_level_inet46_stats data source...
data "vtm_per_node_slm_per_node_service_level_inet46_stats"
"my_per_node_slm_per_node_service_level_inet46_stats" {
    name = "MyPerNodeSlmPerNodeServiceLevelInet46"
}
```

```
# Access with...
```

"\${data.vtm\_per\_node\_slm\_per\_node\_service\_level\_inet46\_stats.my\_per\_node\_slm\_per\_node\_service\_level\_inet46\_stats.celevel\_inet46\_stats.

Field Name	Description
node_port	The port number of this node.
	Type: UInt SNMP name: "perNodeServiceLevelInet46NodePort"
response_max	Maximum response time (ms) in the last second for this SLM class to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perNodeServiceLevelInet46ResponseMax"</li></ul>
response_mean	Mean response time (ms) in the last second for this SLM class to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perNodeServiceLevelInet46ResponseMean"</li></ul>
response_min	Minimum response time (ms) in the last second for this SLM class to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perNodeServiceLevelInet46ResponseMin"</li></ul>
total_conn	Requests handled by this SLM class to this node.
	Type: UInt     SNMP name: "perNodeServiceLevelInet46TotalConn"
total_non_conf	Non-conforming requests handled by this SLM class to this node.
	Type: Ulnt     SNMP name: "perNodeServiceLevelInet46TotalNonConf"

#### vtm nodes per pool node stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/nodes/per\_pool\_node/\*

Per pool node statistics values.

```
# Example usage of vtm_nodes_per_pool_node_stats data source...
data "vtm_nodes_per_pool_node_stats" "my_nodes_per_pool_node_stats" {
    name = "MyNodesPerPoolNode"
}
# Access with...
"${data.vtm_nodes_per_pool_node_stats.my_nodes_per_pool_node_stats.<FIELD_NAME>}"
```

Field Name	Description
bytes_from_node	Bytes received from this node.
	<ul><li>Type: UInt64</li><li>SNMP name: "perPoolNodeBytesFromNode"</li></ul>
bytes_from_node_hi	Bytes received from this node ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeBytesFromNodeHi"</li></ul>
bytes_from_node_lo	Bytes received from this node ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeBytesFromNodeLo"</li></ul>
bytes_to_node	Bytes sent to this node.
	<ul><li>Type: UInt64</li><li>SNMP name: "perPoolNodeBytesToNode"</li></ul>
bytes_to_node_hi	Bytes sent to this node ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeBytesToNodeHi"</li></ul>
bytes_to_node_lo	Bytes sent to this node ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeBytesToNodeLo"</li></ul>
current_conn	Current connections established to a node, includes idle connections.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeCurrentConn"</li></ul>
current_requests	Active connections established to this node, does not include idle connections.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeCurrentRequests"</li></ul>
errors	Number of timeouts, connection problems and other errors for this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeErrors"</li></ul>
failures	Failures of this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeFailures"</li></ul>
idle_conns	Number of idle HTTP connections to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeIdleConns"</li></ul>
I4_stateless_buckets	Number of hash buckets occupied for this node for L4 stateless processing.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeL4StatelessBuckets"</li></ul>

Field Name	Description
new_conn	Requests that created a new connection to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeNewConn"</li></ul>
node_port	The port that this node listens on.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeNodePort"</li></ul>
pkts_from_node	Packets received from this node.
	<ul><li>Type: UInt64</li><li>SNMP name: "perPoolNodePktsFromNode"</li></ul>
pkts_from_node_hi	Packets received from this node ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodePktsFromNodeHi"</li></ul>
pkts_from_node_lo	Packets received from this node ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodePktsFromNodeLo"</li></ul>
pkts_to_node	Packets sent to this node.
	<ul><li>Type: UInt64</li><li>SNMP name: "perPoolNodePktsToNode"</li></ul>
pkts_to_node_hi	Packets sent to this node ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodePktsToNodeHi"</li></ul>
pkts_to_node_lo	Packets sent to this node ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodePktsToNodeLo"</li></ul>
pooled_conn	Requests that reused an existing pooled/keepalive connection rather than creating a new TCP connection.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodePooledConn"</li></ul>
response_max	Maximum response time (ms) in the last second for this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeResponseMax"</li></ul>
response_mean	Mean response time (ms) in the last second for this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeResponseMean"</li></ul>
response_min	Minimum response time (ms) in the last second for this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeResponseMin"</li></ul>

Field Name	Description
state	The state of this node.
	<ul> <li>Type: Enum(String)</li> <li>SNMP name: "perPoolNodeState"</li> <li>Permitted values:         <ul> <li>"alive": alive(1)</li> </ul> </li> </ul>
	"dead": dead(2)
	"unknown": unknown(3)
	"draining": draining(4)
	"drainingtodelete": drainingtodelete(5)
total_conn	Requests sent to this node.
	<ul><li>Type: UInt</li><li>SNMP name: "perPoolNodeTotalConn"</li></ul>

## vtm\_pool\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/pools/\*

Pools statistics values.

```
# Example usage of vtm_pool_stats data source...
data "vtm_pool_stats" "my_pool_stats" {
    name = "MyPool"
}
# Access with...
"${data.vtm_pool_stats.my_pool_stats.<FIELD_NAME>}"
```

Field Name	Description
algorithm	The load-balancing algorithm the pool uses.
	<ul> <li>Type: Enum(String)</li> <li>SNMP name: "poolAlgorithm"</li> <li>Permitted values:         "roundrobin": roundrobin(1)</li> </ul>
	"weightedRoundRobin": weightedRoundRobin(2)
	"perceptive": perceptive(3)
	"leastConnections": leastConnections(4)
	"fastestResponseTime": fastestResponseTime(5)
	"random": random(6)
	"weightedLeastConnections": weightedLeastConnections(7)
bw_limit_bytes_drop	Bytes dropped by this pool due to BW Limits.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "poolBwLimitBytesDrop"</li></ul>

Field Name	Description
bw_limit_bytes_drop_hi	Bytes dropped by this pool due to BW Limits ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "poolBwLimitBytesDropHi"</li></ul>
bw_limit_bytes_drop_lo	Bytes dropped by this pool due to BW Limits ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "poolBwLimitBytesDropLo"</li></ul>
bw_limit_pkts_drop	Number of packets dropped by this pool due to BW Limits.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "poolBwLimitPktsDrop"</li></ul>
bw_limit_pkts_drop_hi	Number of packets dropped by this pool due to BW Limits ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "poolBwLimitPktsDropHi"</li></ul>
bw_limit_pkts_drop_lo	Number of packets dropped by this pool due to BW Limits ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "poolBwLimitPktsDropLo"</li></ul>
bytes_in	Bytes received by this pool from nodes.
	<ul><li>Type: UInt64</li><li>SNMP name: "poolBytesIn"</li></ul>
bytes_in_hi	Bytes received by this pool from nodes ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "poolBytesInHi"</li></ul>
bytes_in_lo	Bytes received by this pool from nodes ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "poolBytesInLo"</li></ul>
bytes_out	Bytes sent by this pool to nodes.
	<ul><li>Type: UInt64</li><li>SNMP name: "poolBytesOut"</li></ul>
bytes_out_hi	Bytes sent by this pool to nodes ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "poolBytesOutHi"</li></ul>
bytes_out_lo	Bytes sent by this pool to nodes ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "poolBytesOutLo"</li></ul>
conns_queued	Total connections currently queued to this pool.
	<ul><li>Type: UInt</li><li>SNMP name: "poolConnsQueued"</li></ul>

Field Name	Description
disabled	The number of nodes in this pool that are disabled.
	<ul><li>Type: Ulnt</li><li>SNMP name: "poolDisabled"</li></ul>
draining	The number of nodes in this pool which are draining.
	<ul><li>Type: UInt</li><li>SNMP name: "poolDraining"</li></ul>
max_queue_time	Maximum time a connection was queued for, over the last second.
	<ul><li>Type: UInt</li><li>SNMP name: "poolMaxQueueTime"</li></ul>
mean_queue_time	Mean time a connection was queued for, over the last second.
	<ul><li>Type: UInt</li><li>SNMP name: "poolMeanQueueTime"</li></ul>
min_queue_time	Minimum time a connection was queued for, over the last second.
	<ul><li>Type: UInt</li><li>SNMP name: "poolMinQueueTime"</li></ul>
nodes	The number of nodes registered with this pool.
	<ul><li>Type: UInt</li><li>SNMP name: "poolNodes"</li></ul>
persistence	The session persistence method this pool uses
	<ul> <li>Type: Enum(String)</li> <li>SNMP name: "poolPersistence"</li> <li>Permitted values:     "none": none(1)</li> </ul>
	"ip": ip(2)
	"rule": rule(3)
	"transparent": transparent(4)
	"applicationCookie": applicationCookie(5)
	"xZeusBackend": xZeusBackend(6)
	"ssl": ssl(7)
queue_timeouts	Total connections that timed-out while queued.
	<ul><li>Type: UInt</li><li>SNMP name: "poolQueueTimeouts"</li></ul>
session_migrated	Sessions migrated to a new node because the desired node was unavailable.
	<ul><li>Type: UInt</li><li>SNMP name: "poolSessionMigrated"</li></ul>

Field Name	Description
state	The state of this pool.
	<ul><li>Type: Enum(String)</li><li>SNMP name: "poolState"</li><li>Permitted values: "active": active(1)</li></ul>
	"disabled": disabled(2)
	"draining": draining(3)
	"unused": unused(4)
	"unknown": unknown(5)
total_conn	Requests sent to this pool.
	<ul><li>Type: UInt</li><li>SNMP name: "poolTotalConn"</li></ul>

#### vtm\_rule\_authenticator\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/rule\_authenticators/\*

Rule authenticators statistics values.

```
# Example usage of vtm_rule_authenticator_stats data source...
data "vtm_rule_authenticator_stats" "my_rule_authenticator_stats" {
    name = "MyRuleAuthenticator"
}
# Access with...
"${data.vtm_rule_authenticator_stats.my_rule_authenticator_stats.<FIELD_NAME>}"
```

Field Name	Description
errors	Number of connection errors that have occurred when trying to connect to an authentication server.
	<ul><li>Type: UInt</li><li>SNMP name: "authenticatorErrors"</li></ul>
fails	Number of times this Authenticator has failed to authenticate.
	<ul><li>Type: UInt</li><li>SNMP name: "authenticatorFails"</li></ul>
passes	Number of times this Authenticator has successfully authenticated.
	<ul><li>Type: UInt</li><li>SNMP name: "authenticatorPasses"</li></ul>
requests	Number of times this Authenticator has been asked to authenticate.
	<ul><li>Type: UInt</li><li>SNMP name: "authenticatorRequests"</li></ul>

## vtm\_rule\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/rules/\*

Rules statistics values.

```
# Example usage of vtm_rule_stats data source...
data "vtm_rule_stats" "my_rule_stats" {
    name = "MyRule"
}
# Access with...
"${data.vtm_rule_stats.my_rule_stats.<FIELD_NAME>}"
```

Field Name	Description
aborts	Number of times this TrafficScript rule has aborted.
	<ul><li>Type: UInt</li><li>SNMP name: "ruleAborts"</li></ul>
discards	Number of times this TrafficScript rule has discarded the connection.
	<ul><li>Type: UInt</li><li>SNMP name: "ruleDiscards"</li></ul>
execution_time_warnings	Number of times this TrafficScript rule has exceeded the execution time warning threshold.
	<ul><li>Type: UInt</li><li>SNMP name: "ruleExecutionTimeWarnings"</li></ul>
executions	Number of times this TrafficScript rule has been executed.
	<ul><li>Type: UInt</li><li>SNMP name: "ruleExecutions"</li></ul>
pool_select	Number of times this TrafficScript rule has selected a pool to use.
	<ul><li>Type: UInt</li><li>SNMP name: "rulePoolSelect"</li></ul>
responds	Number of times this TrafficScript rule has responded directly to the client.
	<ul><li>Type: UInt</li><li>SNMP name: "ruleResponds"</li></ul>
retries	Number of times this TrafficScript rule has forced the request to be retried.
	<ul><li>Type: UInt</li><li>SNMP name: "ruleRetries"</li></ul>

## vtm\_service\_level\_monitor\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/service\_level\_monitors/\*

Service level monitors statistics values.

```
# Example usage of vtm_service_level_monitor_stats data source...
data "vtm_service_level_monitor_stats" "my_service_level_monitor_stats" {
    name = "MyServiceLevelMonitor"
}

# Access with...
"${data.vtm service level monitor stats.my service level monitor stats.<FIELD NAME>}"
```

Field Name	Description
conforming	Percentage of requests associated with this SLM class that are conforming
	<ul><li>Type: UInt</li><li>SNMP name: "serviceLevelConforming"</li></ul>
current_conns	The number of connections currently associated with this SLM class.
	<ul><li>Type: UInt</li><li>SNMP name: "serviceLevelCurrentConns"</li></ul>
is_o_k	Indicates if this SLM class is currently conforming.
	<ul><li>Type: Enum(String)</li><li>SNMP name: "serviceLevelIsOK"</li><li>Permitted values: "notok": notok(1)</li></ul>
	"ok": ok(2)
response_max	Maximum response time (ms) in the last second for this SLM class.
	<ul><li>Type: UInt</li><li>SNMP name: "serviceLevelResponseMax"</li></ul>
response_mean	Mean response time (ms) in the last second for this SLM class.
	<ul><li>Type: UInt</li><li>SNMP name: "serviceLevelResponseMean"</li></ul>
response_min	Minimum response time (ms) in the last second for this SLM class.
	<ul><li>Type: UInt</li><li>SNMP name: "serviceLevelResponseMin"</li></ul>
total_conn	Requests handled by this SLM class.
	Type: UInt SNMP name: "serviceLevelTotalConn"
total_non_conf	Non-conforming requests handled by this SLM class.
	Type: UInt SNMP name: "serviceLevelTotalNonConf"  Type: UInt

# $vtm\_service\_protection\_stats$

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/service\_protection/\*

Service protection statistics values.

```
# Example usage of vtm_service_protection_stats data source...
data "vtm_service_protection_stats" "my_service_protection_stats" {
    name = "MyServiceProtection"
}
# Access with...
"${data.vtm_service_protection_stats.my_service_protection_stats.<FIELD_NAME>}"
```

Field Name	Description
last_refusal_time	The time (in hundredths of a second) since this service protection class last refused a connection (this value will wrap if no connections are refused in more than 497 days).
	<ul><li>Type: UInt</li><li>SNMP name: "serviceProtLastRefusalTime"</li></ul>
refusal_binary	Connections refused by this service protection class because the request contained disallowed binary content.
	<ul><li>Type: UInt</li><li>SNMP name: "serviceProtRefusalBinary"</li></ul>
refusal_conc10_ip	Connections refused by this service protection class because the top 10 source IP addresses issued too many concurrent connections.
	<ul><li>Type: UInt</li><li>SNMP name: "serviceProtRefusalConc10IP"</li></ul>
refusal_conc1_ip	Connections refused by this service protection class because the source IP address issued too many concurrent connections.
	<ul><li>Type: UInt</li><li>SNMP name: "serviceProtRefusalConc1IP"</li></ul>
refusal_conn_rate	Connections refused by this service protection class because the source IP address issued too many connections within 60 seconds.
	<ul><li>Type: UInt</li><li>SNMP name: "serviceProtRefusalConnRate"</li></ul>
refusal_ip	Connections refused by this service protection class because the source IP address was banned.
	<ul><li>Type: UInt</li><li>SNMP name: "serviceProtRefusalIP"</li></ul>
refusal_rfc2396	Connections refused by this service protection class because the HTTP request was not RFC 2396 compliant.
	<ul><li>Type: UInt</li><li>SNMP name: "serviceProtRefusalRFC2396"</li></ul>

Field Name	Description
refusal_size	Connections refused by this service protection class because the request was larger than the defined limits allowed.
	<ul><li>Type: UInt</li><li>SNMP name: "serviceProtRefusalSize"</li></ul>
total_refusal	Connections refused by this service protection class.
	<ul><li>Type: UInt</li><li>SNMP name: "serviceProtTotalRefusal"</li></ul>

## vtm\_cache\_ssl\_cache\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/cache/ssl\_cache

Ssl cache statistics values.

```
# Example usage of vtm_cache_ssl_cache_stats data source...
data "vtm_cache_ssl_cache_stats" "my_cache_ssl_cache_stats" {}

# Access with...
"${data.vtm_cache_ssl_cache_stats.my_cache_ssl_cache_stats.<FIELD_NAME>}"
```

Field Name	Description
entries	The total number of SSL sessions stored in the server cache.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCacheEntries"</li></ul>
entries_max	The maximum number of SSL entries in the server cache.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCacheEntriesMax"</li></ul>
hit_rate	The percentage of SSL server cache lookups that succeeded.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCacheHitRate"</li></ul>
hits	Number of times a SSL entry has been successfully found in the server cache.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCacheHits"</li></ul>
lookups	Number of times a SSL entry has been looked up in the server cache.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCacheLookups"</li></ul>

Field Name	Description
misses	Number of times a SSL entry has not been available in the server cache.
	<ul><li>Type: UInt</li><li>SNMP name: "sslCacheMisses"</li></ul>
oldest	The age of the oldest SSL session in the server cache (in seconds).
	<ul><li>Type: UInt</li><li>SNMP name: "sslCacheOldest"</li></ul>

## vtm\_ssl\_ocsp\_stapling\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/ssl\_ocsp\_stapling

Ssl ocsp stapling statistics values.

```
# Example usage of vtm_ssl_ocsp_stapling_stats data source...
data "vtm_ssl_ocsp_stapling_stats" "my_ssl_ocsp_stapling_stats" {}

# Access with...
"${data.vtm_ssl_ocsp_stapling_stats.my_ssl_ocsp_stapling_stats.<FIELD_NAME>}"
```

Field Name	Description
cache_count	The number of entries in the OCSP stapling cache.
	<ul><li>Type: UInt</li><li>SNMP name: "sslOcspStaplingCacheCount"</li></ul>
counter	The number of outgoing OCSP requests for OCSP stapling.
	<ul><li>Type: UInt</li><li>SNMP name: "sslOcspStaplingCount"</li></ul>
failure_count	The number of failed outgoing OCSP requests for OCSP stapling.
	<ul><li>Type: UInt</li><li>SNMP name: "sslOcspStaplingFailureCount"</li></ul>
good_count	The number of 'good' OCSP responses for OCSP stapling.
	<ul><li>Type: UInt</li><li>SNMP name: "sslOcspStaplingGoodCount"</li></ul>
revoked_count	The number of 'revoked' OCSP responses for OCSP stapling.
	<ul><li>Type: UInt</li><li>SNMP name: "sslOcspStaplingRevokedCount"</li></ul>
success_count	The number of successful outgoing OCSP requests for OCSP stapling.
	<ul><li>Type: UInt</li><li>SNMP name: "sslOcspStaplingSuccessCount"</li></ul>
unknown_count	The number of 'unknown' OCSP requests for OCSP stapling.
	<ul><li>Type: UInt</li><li>SNMP name: "sslOcspStaplingUnknownCount"</li></ul>

## vtm\_cache\_ssl\_session\_cache\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/cache/ssl\_session\_cache

Ssl session cache statistics values.

```
# Example usage of vtm_cache_ssl_session_cache_stats data source...
data "vtm_cache_ssl_session_cache_stats" "my_cache_ssl_session_cache_stats" {}
```

<sup>&</sup>quot;\${data.vtm\_cache\_ssl\_session\_cache\_stats.my\_cache\_ssl\_session\_cache\_stats.<FIELD\_NAME>}"

Field Name	Description
entries	The total number of SSL session persistence entries stored in the cache.  • Type: UInt
	SNMP name: "sslSessionCacheEntries"
entries_max	The maximum number of SSL session persistence entries in the cache.
	<ul><li>Type: Ulnt</li><li>SNMP name: "sslSessionCacheEntriesMax"</li></ul>
hit_rate	The percentage of SSL session persistence lookups that succeeded.
	<ul><li>Type: UInt</li><li>SNMP name: "sslSessionCacheHitRate"</li></ul>
hits	Number of times a SSL session persistence entry has been successfully found in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "sslSessionCacheHits"</li></ul>
lookups	Number of times a SSL session persistence entry has been looked up in the cache.
	<ul><li>Type: Ulnt</li><li>SNMP name: "sslSessionCacheLookups"</li></ul>
misses	Number of times a SSL session persistence entry has not been available in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "sslSessionCacheMisses"</li></ul>
oldest	The age of the oldest SSL session in the cache (in seconds).
	<ul><li>Type: UInt</li><li>SNMP name: "sslSessionCacheOldest"</li></ul>

# vtm\_traffic\_ips\_traffic\_ip\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/traffic\_ips/traffic\_ip/\*

Traffic ip statistics values.

<sup>#</sup> Access with...

```
# Example usage of vtm_traffic_ips_traffic_ip_stats data source...
data "vtm_traffic_ips_traffic_ip_stats" "my_traffic_ips_traffic_ip_stats" {
    name = "MyTrafficIpsTrafficIp"
}
# Access with...
"${data.vtm_traffic_ips_traffic_ip_stats.my_traffic_ips_traffic_ip_stats.<FIELD_NAME>}"
```

Field Name	Description
state	Whether this traffic IP address is currently being hosted by this traffic manager.
	<ul><li>Type: Enum(String)</li><li>SNMP name: "trafficIPState"</li><li>Permitted values:     "raised": raised(1)</li></ul>
	"lowered": lowered(2)
time	The time (in hundredths of a second) since trafficIPState last changed (this value will wrap if the state hasn't changed for 497 days).
	<ul><li>Type: UInt</li><li>SNMP name: "trafficIPTime"</li></ul>

#### vtm\_traffic\_ips\_traffic\_ip\_inet46\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/traffic\_ips/traffic\_ip\_inet46/\*

Traffic ip inet46 statistics values.

```
# Example usage of vtm_traffic_ips_traffic_ip_inet46_stats data source...
data "vtm_traffic_ips_traffic_ip_inet46_stats" "my_traffic_ips_traffic_ip_inet46_stats" {
    name = "MyTrafficIpsTrafficIpInet46"
}

# Access with...
"${data.vtm_traffic_ips_traffic_ip_inet46_stats.my_traffic_ips_traffic_ip_inet46_stats.<FI
ELD NAME>}"
```

Field Name	Description
state	Whether this traffic IP address is currently being hosted by this traffic manager.
	<ul> <li>Type: Enum(String)</li> <li>SNMP name: "trafficIPInet46State"</li> <li>Permitted values:         "raised": raised(1)</li> <li>"lowered": lowered(2)</li> </ul>
time	The time (in hundredths of a second) since trafficIPState last changed (this value will wrap if the state hasn't changed for 497 days).
	<ul><li>Type: UInt</li><li>SNMP name: "trafficIPInet46Time"</li></ul>

## vtm\_cache\_uni\_session\_cache\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/cache/uni\_session\_cache

Uni session cache statistics values.

```
# Example usage of vtm_cache_uni_session_cache_stats data source...
data "vtm_cache_uni_session_cache_stats" "my_cache_uni_session_cache_stats" {}
```

# Access with...

<sup>&</sup>quot;\${data.vtm cache uni session cache stats.my cache uni session cache stats.<FIELD NAME>}"

Field Name	Description
entries	The total number of universal sessions stored in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "uniSessionCacheEntries"</li></ul>
entries_max	The maximum number of universal sessions in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "uniSessionCacheEntriesMax"</li></ul>
hit_rate	The percentage of universal session lookups that succeeded.
	<ul><li>Type: UInt</li><li>SNMP name: "uniSessionCacheHitRate"</li></ul>
hits	Number of times a universal session entry has been successfully found in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "uniSessionCacheHits"</li></ul>
lookups	Number of times a universal session entry has been looked up in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "uniSessionCacheLookups"</li></ul>

Field Name	Description
misses	Number of times a universal session entry has not been available in the cache.
	<ul><li>Type: UInt</li><li>SNMP name: "uniSessionCacheMisses"</li></ul>
oldest	The age of the oldest universal session in the cache (in seconds).
	<ul><li>Type: UInt</li><li>SNMP name: "uniSessionCacheOldest"</li></ul>

#### vtm extras user counters 32 stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/extras/user\_counters\_32

User counters 32 statistics values.

```
# Example usage of vtm_extras_user_counters_32_stats data source...
data "vtm_extras_user_counters_32_stats" "my_extras_user_counters_32_stats" {}

# Access with...
"${data.vtm extras user counters 32 stats.my extras user counters 32 stats.<FIELD NAME>}"
```

Field Name	Description
counter	The value of the user counter.
	<ul><li>Type: UInt</li><li>SNMP name: "userCounterValue"</li></ul>

#### vtm extras user counters 64 stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/extras/user\_counters\_64

User counters 64 statistics values.

```
# Example usage of vtm_extras_user_counters_64_stats data source...
data "vtm_extras_user_counters_64_stats" "my_extras_user_counters_64_stats" {}

# Access with...
"${data.vtm extras user counters 64 stats.my extras user counters 64 stats.<FIELD NAME>}"
```

Field Name	Description
counter	The value of the 64-bit user counter.
	<ul><li>Type: UInt64</li><li>SNMP name: "userCounter64Value"</li></ul>

#### vtm\_virtual\_server\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/virtual\_servers/\*

Virtual servers statistics values.

```
# Example usage of vtm_virtual_server_stats data source...
data "vtm_virtual_server_stats" "my_virtual_server_stats" {
    name = "MyVirtualServer"
}
# Access with...
"${data.vtm_virtual_server_stats.my_virtual_server_stats.<FIELD_NAME>}"
```

Field Name	Description
bw_limit_bytes_drop	Number of bytes dropped by this virtual server due to BW Limits.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "virtualserverBwLimitBytesDrop"</li></ul>
bw_limit_bytes_drop_hi	Number of bytes dropped by this virtual server due to BW Limits ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverBwLimitBytesDropHi"</li></ul>
bw_limit_bytes_drop_lo	Number of bytes dropped by this virtual server due to BW Limits ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverBwLimitBytesDropLo"</li></ul>
bw_limit_pkts_drop	Number of packets dropped by this virtual server due to BW Limits.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "virtualserverBwLimitPktsDrop"</li></ul>
bw_limit_pkts_drop_hi	Number of packets dropped by this virtual server due to BW Limits (high 32bits).
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverBwLimitPktsDropHi"</li></ul>
bw_limit_pkts_drop_lo	Number of packets dropped by this virtual server due to BW Limits ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverBwLimitPktsDropLo"</li></ul>
bytes_in	Bytes received by this virtual server from clients.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "virtualserverBytesIn"</li></ul>
bytes_in_hi	Bytes received by this virtual server from clients ( high 32bits ).
	<ul><li>Type: Ulnt</li><li>SNMP name: "virtualserverBytesInHi"</li></ul>
bytes_in_lo	Bytes received by this virtual server from clients ( low 32bits ).
	Type: Ulnt     SNMP name: "virtualserverBytesInLo"

Field Name	Description
bytes_out	Bytes sent by this virtual server to clients.
	<ul><li>Type: UInt64</li><li>SNMP name: "virtualserverBytesOut"</li></ul>
bytes_out_hi	Bytes sent by this virtual server to clients ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverBytesOutHi"</li></ul>
bytes_out_lo	Bytes sent by this virtual server to clients ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverBytesOutLo"</li></ul>
cert_status_requests	Number of incoming TLS handshakes for this virtual server with certificate status requests.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverCertStatusRequests"</li></ul>
cert_status_responses	Number of incoming TLS handshakes for this virtual server to which certificate status responses were attached.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverCertStatusResponses"</li></ul>
connect_timed_out	Connections closed by this virtual server because the 'connect_timeout' interval was exceeded.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverConnectTimedOut"</li></ul>
connection_errors	Number of transaction or protocol errors in this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverConnectionErrors"</li></ul>
connection_failures	Number of connection failures in this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverConnectionFailures"</li></ul>
current_conn	TCP connections currently established to this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverCurrentConn"</li></ul>
data_timed_out	Connections closed by this virtual server because the 'timeout' interval was exceeded.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverDataTimedOut"</li></ul>
direct_replies	Direct replies from this virtual server, without forwarding to a node.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverDirectReplies"</li></ul>
discard	Connections discarded by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverDiscard"</li></ul>

Field Name	Description
gzip	Responses which have been compressed by content compression.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverGzip"</li></ul>
gzip_bytes_saved	Bytes of network traffic saved by content compression.
	<ul><li>Type: UInt64</li><li>SNMP name: "virtualserverGzipBytesSaved"</li></ul>
gzip_bytes_saved_hi	Bytes of network traffic saved by content compression ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverGzipBytesSavedHi"</li></ul>
gzip_bytes_saved_lo	Bytes of network traffic saved by content compression (low 32bits).
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverGzipBytesSavedLo"</li></ul>
http_cache_hit_rate	Percentage hit rate of the web cache for this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverHttpCacheHitRate"</li></ul>
http_cache_hits	HTTP responses sent directly from the web cache by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverHttpCacheHits"</li></ul>
http_cache_lookups	HTTP requests that are looked up in the web cache by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverHttpCacheLookups"</li></ul>
http_rewrite_cookie	HTTP Set-Cookie headers, supplied by a node, that have been rewritten.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverHttpRewriteCookie"</li></ul>
http_rewrite_location	HTTP Location headers, supplied by a node, that have been rewritten.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverHttpRewriteLocation"</li></ul>
keepalive_timed_out	Connections closed by this virtual server because the 'keepalive_timeout' interval was exceeded.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverKeepaliveTimedOut"</li></ul>
max_conn	Maximum number of simultaneous TCP connections this virtual server has processed at any one time.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverMaxConn"</li></ul>
max_duration_timed_out	Connections closed by this virtual server because the 'max_transaction_duration' interval was exceeded.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverMaxDurationTimedOut"</li></ul>

Field Name	Description
pkts_in	Packets received by this virtual server from clients.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "virtualserverPktsIn"</li></ul>
pkts_in_hi	Packets received by this virtual server from clients ( high 32bits ).
	<ul><li>Type: Ulnt</li><li>SNMP name: "virtualserverPktsInHi"</li></ul>
pkts_in_lo	Packets received by this virtual server from clients ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverPktsInLo"</li></ul>
pkts_out	Packets sent by this virtual server to clients.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "virtualserverPktsOut"</li></ul>
pkts_out_hi	Packets sent by this virtual server to clients ( high 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverPktsOutHi"</li></ul>
pkts_out_lo	Packets sent by this virtual server to clients ( low 32bits ).
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverPktsOutLo"</li></ul>
port	The port the virtual server listens on.
	<ul><li>Type: Ulnt</li><li>SNMP name: "virtualserverPort"</li></ul>
processing_timed_out	Connections closed by this virtual server because the 'timeout' interval was exceeded while waiting for rules or external processing.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverProcessingTimedOut"</li></ul>

Field Name	Description
protocol	The protocol the virtual server is operating.
	<ul> <li>Type: Enum(String)</li> <li>SNMP name: "virtualserverProtocol"</li> <li>Permitted values:         <ul> <li>"http": http(1)</li> </ul> </li> </ul>
	"https": https(2)
	"ftp": ftp(3)
	"imaps": imaps(4)
	"imapv2": imapv2(5)
	"imapv3": imapv3(6)
	"imapv4": imapv4(7)
	"pop3": pop3(8)
	"pop3s": pop3s(9)
	"smtp": smtp(10)
	"ldap": ldap(11)
	"ldaps": ldaps(12)
	"telnet": telnet(13)
	"sslforwarding": sslforwarding(14)
	"udpstreaming": udpstreaming(15)
	"udp": udp(16)
	"dns": dns(17)
	"genericserverfirst": genericserverfirst(18)
	"genericclientfirst": genericclientfirst(19)
	"dnstcp": dnstcp(20)
	"sipudp": sipudp(21)
	"siptcp": siptcp(22)
	"rtsp": rtsp(23)
	"stream": stream(24)
	"l4acceltcp": l4acceltcp(25)
	"l4acceludp": l4acceludp(26)
	"l4accelgeneric": l4accelgeneric(27)
	"l4accelstateless": l4accelstateless(28)
sip_rejected_requests	Number of SIP requests rejected due to them exceeding the maximum amount of memory allocated to the connection.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverSIPRejectedRequests"</li></ul>

Field Name	Description
sip_total_calls	Total number of SIP INVITE requests seen by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverSIPTotalCalls"</li></ul>
total_conn	Formerly provided the number of requests received by this virtual server, now deprecated.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverTotalConn"</li></ul>
total_dgram	UDP datagrams processed by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverTotalDgram"</li></ul>
total_http1_requests	HTTP/1.x Requests received by this virtual server.
	<ul><li>Type: UInt64</li><li>SNMP name: "virtualserverTotalHTTP1Requests"</li></ul>
total_http1_requests_hi	HTTP/1.x Requests received by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverTotalHTTP1RequestsHi"</li></ul>
total_http1_requests_lo	HTTP/1.x Requests received by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverTotalHTTP1RequestsLo"</li></ul>
total_http2_requests	HTTP/2 Requests received by this virtual server.
	<ul><li>Type: UInt64</li><li>SNMP name: "virtualserverTotalHTTP2Requests"</li></ul>
total_http2_requests_hi	HTTP/2 Requests received by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverTotalHTTP2RequestsHi"</li></ul>
total_http2_requests_lo	HTTP/2 Requests received by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverTotalHTTP2RequestsLo"</li></ul>
total_http_requests	HTTP Requests received by this virtual server.
	<ul><li>Type: UInt64</li><li>SNMP name: "virtualserverTotalHTTPRequests"</li></ul>
total_http_requests_hi	HTTP Requests received by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverTotalHTTPRequestsHi"</li></ul>
total_http_requests_lo	HTTP Requests received by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverTotalHTTPRequestsLo"</li></ul>
total_requests	Requests received by this virtual server.
	<ul><li>Type: UInt64</li><li>SNMP name: "virtualserverTotalRequests"</li></ul>

Field Name	Description
total_requests_hi	Requests received by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverTotalRequestsHi"</li></ul>
total_requests_lo	Requests received by this virtual server.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverTotalRequestsLo"</li></ul>
total_tcp_reset	Number of TCP connections reset by this virtual server because the forward traffic cannot be processed.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverL4TCPConnectResets"</li></ul>
total_udp_unreachables	Number of ICMP error responses sent to the client by this virtual server because the forward traffic cannot be processed.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverL4UDPUnreachables"</li></ul>
udp_timed_out	Connections closed by this virtual server because the 'udp_timeout' interval was exceeded.
	<ul><li>Type: UInt</li><li>SNMP name: "virtualserverUdpTimedOut"</li></ul>

## vtm\_cache\_web\_cache\_stats

URI Endpoint: /api/tm/4.0/status/local\_tm/statistics/cache/web\_cache

Web cache statistics values.

```
# Example usage of vtm_cache_web_cache_stats data source...
data "vtm_cache_web_cache_stats" "my_cache_web_cache_stats" {}

# Access with...
"${data.vtm_cache_web_cache_stats.my_cache_web_cache_stats.<FIELD_NAME>}"
```

Field Name	Description
entries	The number of items in the web cache.
	<ul><li>Type: UInt</li><li>SNMP name: "webCacheEntries"</li></ul>
hit_rate	The percentage of web cache lookups that succeeded.
	<ul><li>Type: UInt</li><li>SNMP name: "webCacheHitRate"</li></ul>
hits	Number of times a page has been successfully found in the web cache.
	<ul><li>Type: UInt64</li><li>SNMP name: "webCacheHits"</li></ul>

Field Name	Description
hits_hi	Number of times a page has been successfully found in the web cache (high 32 bits).
	Type: UInt
	SNMP name: "webCacheHitsHi"
hits_lo	Number of times a page has been successfully found in the web cache (low 32 bits).
	<ul><li>Type: UInt</li><li>SNMP name: "webCacheHitsLo"</li></ul>
lookups	Number of times a page has been looked up in the web cache.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "webCacheLookups"</li></ul>
lookups_hi	Number of times a page has been looked up in the web cache (high 32 bits).
	<ul><li>Type: UInt</li><li>SNMP name: "webCacheLookupsHi"</li></ul>
lookups_lo	Number of times a page has been looked up in the web cache (low 32 bits).
	<ul><li>Type: UInt</li><li>SNMP name: "webCacheLookupsLo"</li></ul>
max_entries	The maximum number of items in the web cache.
	<ul><li>Type: UInt</li><li>SNMP name: "webCacheMaxEntries"</li></ul>
mem_maximum	The maximum amount of memory the web cache can use in kilobytes.
	<ul><li>Type: UInt</li><li>SNMP name: "webCacheMemMaximum"</li></ul>
mem_used	Total memory used by the web cache in kilobytes.
	<ul><li>Type: UInt</li><li>SNMP name: "webCacheMemUsed"</li></ul>
misses	Number of times a page has not been found in the web cache.
	<ul><li>Type: UInt64</li><li>SNMP name: "webCacheMisses"</li></ul>
misses_hi	Number of times a page has not been found in the web cache (high 32 bits).
	<ul><li>Type: UInt</li><li>SNMP name: "webCacheMissesHi"</li></ul>
misses_lo	Number of times a page has not been found in the web cache (low 32 bits).
	<ul><li>Type: UInt</li><li>SNMP name: "webCacheMissesLo"</li></ul>

Field Name	Description
oldest	The age of the oldest item in the web cache (in seconds).
	<ul><li>Type: UInt</li><li>SNMP name: "webCacheOldest"</li></ul>
url_store_allocated	Amount of allocated space in the web cache URL store.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "webCacheURLStoreAllocated"</li></ul>
url_store_free	Amount of free space in the web cache URL store.
	<ul><li>Type: UInt64</li><li>SNMP name: "webCacheURLStoreFree"</li></ul>
url_store_size	Total amount of space in the web cache URL store.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "webCacheURLStoreSize"</li></ul>
url_store_total_allocations	Total number of allocations for the web cache URL store.
	<ul><li>Type: UInt64</li><li>SNMP name: "webCacheURLStoreTotalAllocations"</li></ul>
url_store_total_failures	Total number of allocation failures for the web cache URL store.
	<ul><li>Type: Ulnt64</li><li>SNMP name: "webCacheURLStoreTotalFailures"</li></ul>
url_store_total_frees	Total number of blocks freed in the web cache URL store.
	<ul><li>Type: UInt64</li><li>SNMP name: "webCacheURLStoreTotalFrees"</li></ul>

# **System Information**

data "vtm\_state" "state\_information" {}

System information data sources allow Terraform to access information about the current state of a Traffic Manager, including errors and service statuses.

```
vtm_backups_full

URI Endpoint: /api/tm/4.0/status/local_tm/backups/full/*

Full backups.

# Example usage of vtm_backups_full data source...
data "vtm_backups_full" "my_backups_full" {
    name = "MyBackupsFull"
}

# Access with...

"${data.vtm_backups_full.my_backups_full.<FIELD_NAME>}"
```

Property	Description
name	Name of the object
	<ul><li>Type: string</li><li>Required: true</li></ul>
backup_description	Description of the backup
	Type: String
backup_time_stamp	Time the backup was created. Expressed as a UTC value.
	• Type: Int
backup_version	Version of Brocade vTM used to create the backup
	Type: String

#### vtm\_information

URI Endpoint: /api/tm/4.0/status/local\_tm/information

Static information for the system.

```
# Example usage of vtm_information data source...
data "vtm_information" "my_information" {}

# Access with...
"${data.vtm information.my information.<FIELD NAME>}"
```

Property	Description
information_tm_version	Version number of the Traffic Manager instance.
	Type: String
information_uuid	The universally unique identifier for the Traffic Manager instance.  • Type: String

#### vtm\_state

URI Endpoint: /api/tm/4.0/status/local\_tm/state

State information for the Brocade vTM.

```
# Example usage of vtm_state data source...
data "vtm_state" "my_state" {}

# Access with...
"${data.vtm_state.my_state.<FIELD_NAME>}"
```

Property	Description
data_plane_acceleration_capa ble	Whether or not the traffic manager is capable of running in Data Plane Acceleration Mode.
	· Type: Boolean
data_plane_acceleration_confi gured	Whether or not the traffic manager configuration requests Data Plane Acceleration Mode.
	· Type: Boolean
data_plane_acceleration_failed _to_start	Whether or not the traffic manager failed to start Data Plane Acceleration Mode.
	· Type: Boolean
data_plane_acceleration_runni ng	Whether or not the traffic manager is running in Data Plane Acceleration Mode.
	· Type: Boolean
state_error_level	The error_level of the traffic manager.
	<ul><li>Type: Enum(String)</li><li>Permitted values: "ok": System has no problems</li></ul>
	"warn": System has minor issues
	"error": System has major issues
	"fatal": System has issues which causes it to die/crash/fail to startup
state_errors	List of configuration errors for the traffic manager
	Type: Set(String)
state_failed_nodes	A table of nodes which have failed on the traffic manager
	· Type: Table
	Required: false
	<ul> <li>Primary key:</li> <li>node (String): A node which has failed (Required)</li> </ul>
	• Sub keys:
	- pools (Set(String)): List of pools which use this node.
state_failed_nodes_json	A Traffic Manager REST-compatible JSON representation of the "state_failed_nodes" table property. Use this field with the "vtm_state_failed_nodes_table" data source for dynamic table generation from input variables.
	<ul><li>Type: String</li><li>Required: false</li><li>Default value: <none></none></li></ul>
state_license	Current active license or Developer_Mode
	• Type: String

Property	Description
state_pools	<ul> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>name (String): Name of the pool (Required)</li> </ul> </li> <li>Sub keys: <ul> <li>failure_pool (String): Failure pool associated with this pool.</li> <li>active_nodes (Set(String)): List of nodes which are in the active state.</li> <li>draining_nodes (Set(String)): List of nodes which are in the draining state.</li> <li>disabled_nodes (Set(String)): List of nodes which are in the disabled state.</li> </ul> </li> </ul>
state_pools_json	A Traffic Manager REST-compatible JSON representation of the "state_pools" table property. Use this field with the "vtm_state_pools_table" data source for dynamic table generation from input variables.  • Type: String • Required: false • Default value: <none></none>
state_tip_errors	List of traffic IP errors for the traffic manager
	Type: Set(String)
state_virtual_servers	<ul> <li>A table of virtual server status</li> <li>Type: Table</li> <li>Required: false</li> <li>Primary key:  - name (String): Name of the virtual server (Required)</li> <li>Sub keys:  - pool (String): Pool associated with this virtual server.  - port (UInt): Port the virtual server listens on.  - throughput (UInt64): Through put for the virtual server.  - ts_redirect_pools (Set(String)): List of pools which may be selected by Traffic Script Request Rules.</li> </ul>
state_virtual_servers_json	A Traffic Manager REST-compatible JSON representation of the "state_virtual_servers" table property. Use this field with the "vtm_state_virtual_servers_table" data source for dynamic table generation from input variables.  Type: String Required: false Default value: <none></none>

## **Table Field Data Sources**

When hard-coding a Terraform template, you can include nested data structures that represent the table structures used by some Traffic Manager configuration fields. For example, the "nodes\_table" field of the "vtm\_pool" resource can have multiple rows specified as shown in the code sample that follows:

```
resource "vtm_pool" "my_pool" {
    name = "MyPool"
    nodes_table {
        node = "192.0.2.1:80"
        state = "active"
    }
    nodes_table {
        node = "192.0.2.2:80"
        state = "active"
    }
    nodes_table {
        node = "192.0.2.3:80"
        state = "disabled"
    }
}
```

To add a new row to the "nodes\_table" field through this method, add another "nodes\_table {}" block with the relevant field values. Often, however, it is desirable to assign configuration data to a template using input variables, although currently there is no supported method for passing in nested structures.

To facilitate the use-case of passing table configuration into a template through input variables, the Traffic Manager provides table field data sources that can accept standard list variables as inputs to each column of the table field. To identify the corresponding table property, each table field data source uses the naming convention "<RESOURCE\_NAME>\_<TABLE\_FIELD\_NAME>\_table". Each data source supports the same fields, with the same default values, as the corresponding table and returns a JSON string that can be supplied to a configuration resource. Each data source also contains a "json" field that automatically computes the properly-formatted JSON representation of the table row. These json values can then be assembled into a JSON list and assigned to a special field on the resource object called "<TABLE\_FIELD\_NAME>\_json".

For example, using the "vtm\_pool" -> "nodes\_table" data from the preceding code sample, use the table field data source "vtm\_pool\_nodes\_table\_table" to apply the same configuration through input variables:

```
# In the terraform.tfvars file (or equivalent through the command line)
node_list = ["192.0.2.1:80", "192.0.2.2:80", "192.0.2.3:80"]
node_state_list = ["active", "active", "disabled"]

# In the Terraform template...
variable "node_list" {
   type = list
}

variable "node_state_list" {
   type = list
}

data "vtm_pool_nodes_table_table" "nodes_table" {
   count = "${length(var.node_list)}"
   node = "${var.node_list[count.index]}"
   state = "${var.node_state_list[count.index]}"
}

resource "vtm_pool" "my_pool" {
```

```
name = "MyPool"
nodes_table_json = "[${join(",", data.vtm_pool_nodes_table_table.nodes_table.*.json)}]"
}
```

The following list contains all available table field data sources:

- vtm\_action\_arguments\_table
- vtm\_appliance\_nat\_many\_to\_one\_all\_ports\_table
- vtm\_appliance\_nat\_many\_to\_one\_port\_locked\_table
- vtm\_appliance\_nat\_one\_to\_one\_table
- vtm\_appliance\_nat\_port\_mapping\_table
- vtm\_custom\_string\_lists\_table
- vtm\_glb\_service\_dnssec\_keys\_table
- vtm\_glb\_service\_location\_settings\_table
- vtm\_global\_settings\_appliance\_returnpath\_table
- vtm\_log\_export\_metadata\_table
- vtm\_monitor\_arguments\_table
- vtm\_pool\_nodes\_table\_table
- vtm\_state\_failed\_nodes\_table
- vtm\_state\_pools\_table
- vtm state virtual servers table
- vtm\_traffic\_ip\_group\_ip\_mapping\_table
- vtm\_traffic\_manager\_appliance\_card\_table
- vtm\_traffic\_manager\_appliance\_sysctl\_table
- vtm\_traffic\_manager\_hosts\_table
- vtm\_traffic\_manager\_if\_table
- vtm\_traffic\_manager\_ip\_table
- vtm\_traffic\_manager\_routes\_table
- vtm\_traffic\_manager\_trafficip\_table
- vtm\_user\_group\_permissions\_table
- vtm\_virtual\_server\_ocsp\_issuers\_table
- vtm\_virtual\_server\_profile\_table
- vtm\_virtual\_server\_server\_cert\_host\_mapping\_table

# Example Deployment Template

This chapter contains an example template to demonstrate deployment of your Traffic Manager infrastructure through the Terraform provider.

```
provider "vtm" {
  base url = "https://192.0.2.100:9070/api"
   username = "admin"
   password = "admin"
   verify ssl cert = false
#####################
# TIP GROUPS
########################
resource "vtm_traffic_ip_group" "web_tip" {
   name = "web tip"
   enabled = true
   ipaddresses = ["192.0.2.200"]
   machines = ["192.0.2.250"]
####################
####################
resource "vtm pool" "html pool" {
   name = "html pool"
   load balancing algorithm = "weighted least connections"
   nodes table {
     node = "192.0.2.10:80"
      weight = 1
   nodes table {
      node = "192.0.2.11:80"
      weight = 3
   nodes table {
      node = "192.0.2.12:80"
      weight = 3
      state = "disabled"
resource "vtm pool" "images pool" {
   name = "images pool"
   nodes table {
      node = "192.0.2.20:80"
```

```
nodes table {
      node = "192.0.2.21:80"
}
####################
# RULES
####################
resource "vtm rule" "use images pool" {
  name = "UseImagesPool"
   content = << EOF
if(http.getPath() == "/images") {
   pool.use("${vtm pool.images pool.name}");
}
EOF
}
resource "vtm rule" "redirect to https" {
  name = "RedirectToHTTPS"
   content = <<EOF
$hostHeader = http.getHostHeader();
http.redirect("https://" . $hostHeader);
EOF
}
#####################
# SSL CERTS
#####################
resource "vtm server key" "ssl cert" {
  name = "SSL-Cert"
          = ""
  note
   private = <<EOF</pre>
----BEGIN RSA PRIVATE KEY----
MIIEoqIBAAKCAQEApEPR1K+xJbQfUen19H4nLEkQaH5L8/9F+pcjJW14EdlSkI3s
6bPe+eGtWf0XSzDXzOqAufERWrKyhw21c+UYoTA64i43T9nwvlRtxXxcok+VqmqC
HMCT5V7d82DKXnEEE6J5LwmHo48MsaQsBrjeyGVA8n40JDoM3qC1IlYxEoqouRf8
5eYWYAuqL1PSnMT71fZy6VUAaeFRVRwREc3RFxkKa9GEraCaDGp7jfmdrNH1A8Pn
ns3um6kWuRHIliewFhUmc1qTxoQurVTtQh/FQViA6UbQtVCcScYarjqo9dqcuz7R
ABCEBnTx7gcmDeB6VR7luN3MGTc8gupJOjNEawIDAQABAoIBAHl+s8/ulu7VJ+k1
P+EzQZQOwnUXHORuZfrvuI4hRpKlE91ZK+a7JGvcEJSjjowNpz+oHufotrZHv6YG
bLQ4uZvXCWZrWnvULa0I01wjHHzssj0mo+/SPFGFdlJhv6xUmPhQzqMMwGcoEfJ+
BBZAvH6p7Xyt/bDhws0TPoYUDB2yg0VN0lgdjg3S/xR2od8ggZBWow5DV3S0j5ta
QlLojcDqHh6MQ1VOHIUHhillHUKuhlHLhukUHUKhkHKLldMPUrqhmJCaGVSDGr9+
2pjPHz04fp7CZ264rmUyHCGhwhjz4FH1KqkVM5LxoKhbOobwivhrhI/g4skgPxfb
Y71wxsECqYEA2JqEzk6tnCZO8UfiR+FSvCLWmFJAlHuFasUy8B0jpZIlRNxt88iZ
BhsHIJadC09fmMF6WdE1KTZgNnMnm675FDSSKjk12DhGzU/zRqaBh0NE/Lemqe8/
wwn3oLd3Z++zcRJj7P6NCoQN8BEIJ0voiqje+ppEkumfTQ8VEHxGEuECgYEAwiaN
F4W5Z0Y2EEnkwbz1w+Fzaur0q3balipfjt/Up4xWDnsMdP7xPzny2rGzfqf0pU0F
dRR2YwXGhAcTMpo+Nblq9/0YpJ500RDxMMYEj8bYjTaEFJQ4a7SSvki35pFM0/pT
smhyWA04U/ttbs3+XosN335JsbcopZfT3zF3zMsCqYBWDniCXAJqs1vURAJ1GuKb
```

e6AV30BnfnhxBq8Jdhpus5V5Obe6D661HVIEobL+BmhuMhlhzFy55i/jeq9ua398

```
p7pn/x998Yb0FlsLbCa0zoZ/fpyKklOcM76eraaUtklumKb5R95UGknLY4kAzAk1
50jJuzeZw5cWr/JnnWjeIQKBqE09explmBpPI4kdbMXrADeaxQk/SmHW8iWV3AiC
Yh76RO5j49PT7XSDAGwjEE8OQbccAsdOib7heFXkXq3eEWvcQYjHh3tOkxjtzZbi
4MO2j0a27ps1UMEAyPStB4TSP6eByrSKuxruv38h4yqXB2Djn3RP0M/EF4axvZfp
HUk7AoGAL2OaOtwy51k/Oc6bwuPjTAR0wmBX9zelgsLIPiON2jHY287syVzh71Pm
vQGRYZlbGMseXj++s9nQJ24qLTokX2FwGioKvXwFX1ujah7ccJR9iVEwKpQMtDY5
cTiUZkme5oO3Idw6IO115A2EB1/BPpoWBP0M+y2BQYuTGk8F2LU=
----END RSA PRIVATE KEY----
EOF
  public = <<EOF</pre>
----BEGIN CERTIFICATE----
MIIDIDCCAgigAwIBAgIJAMD7f7Ux921VMA0GCSqGSIb3DQEBCwUAMD4xCzAJBgNV
BAYTAkdCMRAwDqYDVQQHEwdkYXNkYXNkMQOwCwYDVQQKEwRCbGFoMQ4wDAYDVQQD
EwVhLmIuYzAeFw0xODAxMjUyMzI3MDNaFw0yODAxMjUyMzI3MDNaMD4xCzAJBgNV
BAYTAkdCMRAwDqYDVQQHEwdkYXNkYXNkMQOwCwYDVQQKEwRCbGFoMQ4wDAYDVQQD
EwVhLmIuYzCCASIwDQYJKoZIhvcNAQEhkhdakdhJLUihiQoCggEBAKRD0ZSvsSW0
H1Hp5fR+JyxJEWERWEewfrRtIyVteBHZUpCN7Omz3vnhrVn9F0sw18zqgLnxEVqy
socNtXPlGKEwOuIuN0/Z8L5UbcV8XKJPlapqqhzAk+Ve3fNqyl5xBBOieS8Jh6OP
DLGkLAa43shlQPJ+NCQ6DN6qtSJWMRKKqLkX/OXmFmALoC9T0pzE+9X2culVAGnh
UVUcERHN0RcZCmvRhK2gmgxqe435nazR9QPD557N7pupFrkRyJYnsBYVJnNYE8aE
Lq1U7UIfxUFYg0lG0LVQnEnGGq46qPXYHLs+0QAQhAZ08e4HJg3gelUe5bjdzBk3
PILqSTozRGsCAwEAAaMhMB8wHQYDVR0OBBYEFOsQUOxzga482TRQfgcvWsOXHu3k
MA0GCSqGSIb3DQEBCwUAA4IBAQAOufUIugke4ZHRAXYmgM5cUX1MbBUs5S71u+Ao
79RfGkDL1kfvPdAoQx1/EoWc7LRIzvbuIZu6BiarU+/Te6mirmjF+dFdCfEka7cY
ZR5/BvU/+xJNEFDz2bEL0f4LTKnEiloEcUsHAt3vaqRdBGNt3vvpJ5FjyaDXjmpA
idvAjkqXEbUUBqt0kWuaQU8CDCv5FiGr9XhmK8YnoABCsyALbF+NP41EyUfZzt0Z
bj25+V9mexgCGRR6HJI9whhz33v51SXjxlAX5vsDiXRhfhLST7MBGamE6ngew2k9
cMbhPHfTIYYM1ijagFU/LEXOQ6jTieldVIvC0KVSue7+eQtn
----END CERTIFICATE----
EOF
   request = ""
#####################
# VIRTUAL SERVERS
#####################
resource "vtm virtual server" "http vs" {
   name = "HTTP"
   enabled = true
   pool = "discard"
   port = 80
   listen on any = false
   listen on traffic ips = ["${vtm traffic ip group.web tip.name}"]
   request rules = [
      "${vtm rule.use images pool.name}",
      "${vtm rule.redirect to https.name}",
   web cache enabled = true
   web cache refresh time = 30
resource "vtm virtual server" "https vs" {
```

name = "HTTPS"

```
enabled = true
pool = "${vtm_pool.html_pool.name}"
port = 443
listen_on_any = false
listen_on_traffic_ips = ["${vtm_traffic_ip_group.web_tip.name}"]
ssl_decrypt = true
ssl_server_cert_default = "${vtm_server_key.ssl_cert.name}"
}
```