


Command-line reference for Warteschlangensimulator

ALEXANDER HERZOG (alexander.herzog@tu-clausthal.de)



This reference refers to version 4.3.0 of Warteschlangensimulator.
Download address: <https://github.com/A-Herzog/Warteschlangensimulator/>.

Inhaltsverzeichnis

1	General information	3
2	List of commands	5
2.1	Benchmark	5
2.2	BuildCLIReference	5
2.3	BuildElementGroupImages	5
2.4	BuildLaTeXReference	5
2.5	Filter	6
2.6	GC	6
2.7	Help	6
2.8	Optimizer	6
2.9	ParameterSeriesVarianceAnalysis	6
2.10	Parameterseries	7
2.11	ParameterseriesTable	7
2.12	Report	7
2.13	Reset	7
2.14	Server	7
2.15	ServerLimited	8
2.16	ServerWeb	8
2.17	SetMaxThreads	8
2.18	SetNUMAMode	8
2.19	Simulation	8
2.20	Version	8

Kapitel 1

General information

Warteschlangensimulaktor is a Java program, i.e. a Java runtime environment is required for execution. If this is available, the simulator can be started with the following command:

```
java -jar Simulator.jar
```

If the file name of a model, statistics, parameter series or optimizer file is appended to this command line separated by a space, the file will be loaded immediately after the program starts.

Kapitel 2

List of commands

Alternatively, Warteschlangensimulator can be invoked with one of the commands described in the following sections. In this case no program window will be displayed, but all output is done directly to the command line. The calling scheme of the commands is as follows:

```
java -jar Simulator.jar Command OptionsForCommand
```

All commands described in the following can also be tried out directly via the graphical program interface using the command „Execute command-line command...“ in the „Extras“ menu.

2.1 Benchmark

Performs a speed test of the computer.

The command expects zero or one additional parameters.
If a parameter is passed, this is either the maximum number of threads to be used, or the file name of the model to be used.

2.2 BuildCLIReference

Generates LaTeX code from the command line help.

The command expects two additional parameters:
1. Language „en“ or „de“
2. Output folder for the LaTeX

2.3 BuildElementGroupImages

Generates per element group an image in the desktop folder.

The command expects one additional parameter:
1. Language „en“ or „de“

2.4 BuildLaTeXReference

Generates LaTeX code from the html-based station help.

The command expects two additional parameters:

1. Language „en“ or „de“
2. Output folder for the LaTeX and image files

2.5 Filter

Filter statistic file.

The command expects exactly three additional parameters:

1. Name of the input statistic file
 2. Name of the input filter configuration file
 3. Name of the output file which will contain the filtered results
- If the output file already exists, the new results will be added.
Otherwise the file will be created.

2.6 GC

Lists the currently active garbage collectors.

This command expects no additional parameters.

2.7 Help

Shows this help.

This command expects one or no additional parameters.

If a command is entered as additional parameter, the help information for this command is displayed.
Otherwise a list with all available commands is displayed.

2.8 Optimizer

Starts a model optimization.

This command expects exactly two additional parameters:

1. Input model file
 2. Optimizer configuration file
- Both input files have to exist.

2.9 ParameterSeriesVarianceAnalysis

Creates a parameter series configuration for a variance analysis

This command expects three or four additional parameters:

1. Input model file
2. Output parameter series file
3. Number of repetitions or the model
4. New value for the number of arrivals (optional)

The input file has to exist.

The output has to be non-existent.

2.10 Parameterseries

Run a parameter series simulation.

This command expects exactly two additional parameters:

1. Input parameter series file
2. Output parameter series file

The input file has to exist.

The output has to be non existent.

2.11 ParameterseriesTable

Exports the results table of a parameter series.

This command expects exactly two additional parameters:

1. Input parameter series file
2. Output table file

The input file has to exist.

The output has to be non existent.

2.12 Report

Exports the whole report or a part of it.

This command expects exactly three additionall parameters:

1. „Inline“, „SingleFiles“, „List“, „Text“, „PDF“ or a list entry, depending if
 - a) a html report with inline images,
 - b) a html teport with separate images,
 - c) an overview of all available individual documents,
 - d) a docx report
 - e) a pdf report or
 - f) an individual document is to be reported.
2. File name of the input file
3. File name of the output file

2.13 Reset

Resets the program configuration.

Resets the configuration of the simulator.

Only the entered license keys will be kept.

2.14 Server

Starts the program as simulation server.

This command expects 0 to 2 additional parameters.

If these parameters exist they have the following meaning:

1. Port to be used

2. Password for encrypted data transfer

If no parameters are specified, the simulator will ask for the port via the console.

2.15 ServerLimited

Starts the program as simulation server.

This command expects 0 to 2 additional parameters.

If these parameters exist they have the following meaning:

1. Port to be used
2. Password for encrypted data transfer

If no parameters are specified, the simulator will ask for the port via the console.

The server will limit the number of simultaneous requests depending on the number of available CPU cores.

2.16 ServerWeb

Starts the program as web-based simulation server.

This command expects one additional parameter:
the port to be used.

2.17 SetMaxThreads

Set the maximum number of threads

The function expects the maximum number of threads to be used as parameter.
Values less or equal 0 will be interpreted as unlimited.

2.18 SetNUMAMode

Set NUMA mode

The function expects a „1“ or a „0“ as parameter.

2.19 Simulation

Start a simulation run.

This command expects exactly two additional parameters:

1. Input model file
2. Output statistic file

The input file has to be existent, the output has to be non existent.

2.20 Version

Displays the current version number.

Outputs only the version number of the Warteschlangensimulators.
No further processing will be done.