
### x86 Initial Booting Sequence

Advanced Operating Systems and Virtualization
Alessandro Pellegrini
A.Y. 2017/2018



## The whole sequence at a glance







### **Boot Sequence**

BIOS/UEFI

The actual Hardware Startup

Bootloader Stage 1

Executes the Stage 2 bootloader (skipped in case of UEFI)

Bootloader Stage 2

Loads and starts the Kernel

Kernel Startup

The Kernel takes control of and initializes the machine (machine–dependent operations)

Init

First process: basic environment initialization (e.g., SystemV Init, systemd)

Runlevels/Targets

Initializes the user environment (e.g., single-user mode, multiuser, graphical, ...)





### Hardware Power Sequences: The Pre-Pre-Boot

- When someone pushes the power button, the CPU can't simply jump up and start fetching code from flash memory
- The hardware waits for the power supply to settle to its nominal state
- Additional voltages must be supplied:
  - On x86 systems: 1.5, 3.3, 5, and 12 V
  - Power Sequencing: these must be provided in a particular order






### Hardware Power Sequences: The Pre-Pre-Boot

- The power is sequenced by controlling analog switches, typically field-effect transistors
- The sequence is often driven by a Complex Program Logic Device (CPLD)
- Platform clocks are derived from a small number of input clock and oscillator sources.
  - The devices use phase-locked loop circuitry to generate the derived clocks used for the platform.
  - These clocks take time to converge.





### Hardware Power Sequences: The Pre-Pre-Boot








### Initial life of the System

- The power-sequencing CPLD can de-assert the reset line to the processor
- At this point, the system is in a very *basic state*:
  - Caches are disabled
  - The Memory Management Unit (MMU) is disabled
  - The CPU is executing in **Real Mode** (8086-compatible)
  - Only one core can run actual code
  - Nothing is in RAM (what to execute?)





## Segmented Memory



logical address = <seg.id : offset> (es. <A : 0x10>)



## Segmentation-based addressing


- There are 4 basic 16-bit segment registers:
  - CS: code segment
  - DS: data segment
  - SS: stack segment
  - ES: extra segment (to be used by the programmer)
- Intel 80386 (1985) added two new registers
  - FS and GS, with no predefined usage





## Segmentation-based addressing

The CPU resolves addresses as:







### Segmentation Nowadays

- Segmentation is still present and always enabled
- Each instruction that touches memory implicitly uses a segment register:
  - a jump instruction uses CS
  - a push instruction uses SS
- Most segment registers can be loaded using a mov instruction
- CS can be loaded only with a jmp or a call




#### x86 Real Mode

- 16-bit instruction execution mode
- 20-bit segmented memory address space
  - 1 MB of total addressable memory
- Address in segment registers is the 16-bits higher part
- Each segment can range from 1 byte to 65,536 bytes (16-bit offset)





## Real Mode Addressing Resolution







Addressing in x86 Real Mode

FFFF: FFFF Segment 3 Segment address: 0x28C0 Start of segment 3 Address: 0x28C0:0000 - or -0x2143:0x77D0 Linear address: 0x28C00 Growing Start of segment Segment 2 Physical Address: 0x2143:0000 Segment address: 0x2143 Linear address: 0x21430 Addresses Segment 1 Segment address: 0x0CEF Start of segment Address: 0x0CEF:0000 Linear address: 0x0CEF0 0000:0000





Addressing in x86 Real Mode

Segment 3 Segment address: 0x28C0 Start of segment 3 Address: 0x28C0:0000 - or -0x2143:0x77D0 Linear address: 0x28C00 Start of segment Segment 2 Address: 0x2143:0000 Segment address: 0x2143 Linear address: 0x21430 Segment 1 Segment address: 0x0CEF Start of segment Address: 0x0CEF:0000 Linear address: 0x0CEF0

FFFF:FFFF

Weren't they 20 bits?

Growing Physical Addresses

0000:0000

Main memory



Addressing in x86 Real Mode

Segment 3 Segment address: 0x28C0 Start of segment 3 Address: 0x28C0:0000 - or -0x2143:0x77D0 Linear address: 0x28C00 Start of segment Segment 2 Address: 0x2143:0000 Segment address: 0x2143 Linear address: 0x21430 Segment 1 Segment address: 0x0CEF Start of segment Address: 0x0CEF:0000 Linear address: 0x0CEF0

FFFF:FFFF

Weren't they 20 bits?

Largest address is FFFFF!

Growing Physical Addresses

0000:0000

Main memory



#### First Fetched Instruction

- The PC runs in a *quasi*-real mode
  - Bit 20 is shortcircuited to 1
- The first fetched address is F000: FFF0
  - This is known as the reset vector
  - On IBM PCs this is mapped to a ROM: the BIOS
  - This gives space only to 16 bytes from the top of ROM memory:

```
ljmp $0xf000,$0xe05b
```

This is where the BIOS code is loaded



### **BIOS Operations**

- The BIOS first looks for video adapters that may need to load their own routines
  - These ROMs are mapped from C000:0000 to C780:0000
- Power-On Self-Test (POST)
  - Depends on the actual BIOS
  - Often involves testing devices (keyboard, mouse)
  - Video Card Initialization
  - RAM consistency check





### **BIOS Operations**

- Boot configuration loaded from CMOS (64 bytes)
  - For example, the *boot order*
- Shadow RAM initialization
  - The BIOS copies itself into RAM for faster access
- The BIOS tries to identify the Stage 1 bootloader, (512 bytes) using the specified boot order and loads it to memory at 0000:7c00
- Control is given with:

ljmp \$0x0000,\$0x7c00





### The RAM after the BIOS startup

**BIOS ROM** 

16-bit devices, expansion ROM

**VGA** Display

Low Memory

———— 0x00100000 **(1 Mb)** 

← 0x000F0000 (960 Kb)

0x000A0000 (640 Kb)

The bootloader is loaded here

\_\_\_\_\_ 0x0000000

The only available "RAM" in the early days





### **Boot Sequence**

**BIOS/UEFI** 

The actual Hardware Startup

Bootloader Stage 1

Executes the Stage 2 bootloader (skipped in case of UEFI)

Bootloader Stage 2

Loads and starts the Kernel

Kernel Startup

The Kernel takes control of and initializes the machine (machine–dependent operations)

Init

First process: basic environment initialization (e.g., SystemV Init, systemd)

Runlevels/Targets

Initializes the user environment (e.g., single-user mode, multiuser, graphical, ...)






#### The Boot Sector

- The first device sector keeps the so called Master Boot Record (MBR)
- This sector keeps executable code and a 4-entry partition table, identifying different device partitions (in terms of its positioning on the device)
- In case the partition is extended, then it can additionally keep up to 4 sub-partitions (extended partition)





### The Device Organization



- Boot sector: it can contain additional boot code
- Extended partition boot record



- This implements the Stage 1 bootloader
- (Less than) 512 bytes can be used to load the operating system

Offset	Size (bytes)	Description
0	436 (to 446, if you need a little extra)	MBR Bootstrap (flat binary executable code)
0x1b4	10	Optional "unique" disk ID <sup>1</sup>
0x1be	64	MBR Partition Table, with 4 entries (below)
0x1be	16	First partition table entry
0x1ce	16	Second partition table entry
0x1de	16	Third partition table entry
0x1ee	16	Fourth partition table entry
0x1fe	2	(0x55, 0xAA) "Valid bootsector" signature bytes





- The initial bytes of the MBR can contain the *BIOS Parameter Block* (BPB)
- It is a data structure describing the physical layout of a data storage volume
  - It is used, e.g., by FAT16, FAT32, and NTFS
- This eats up additional space, and must be placed *at the beginning* of the MBR!
  - How to execute the code?





```
.code16
                               Sides: .short 2
 .text
                               HiddenSectors: .int 0
.globl start;
                               LargeSectors: .int 0
                               DriveNo: .short 0
                               Signature: .byte 41 #41 = floppy
start:
jmp .stage1 start
                               VolumeID: .int 0x00000000
                               VolumeLabel: .string "myOS"
OEMLabel: .string "BOOT"
                               FileSystem: .string "FAT12"
BytesPerSector: .short 512
SectorsPerCluster: .byte 1
                                .stage1 start:
ReservedForBoot: .short 1
                                   cli # Disable interrupts
NumberOfFats: .byte 2
                                   xorw %ax, %ax # Segment zero
RootDirEntries: .short 224
                                   movw %ax, %ds
Logical Sectors: .short 2880
                                   movw %ax, %es
MediumByte: .byte 0x0F0
                                   movw %ax, %ss
SectorsPerFat: .short 9
SectorsPerTrack: .short 18
```



```
.code16
                               Sides: .short 2
 .text
                               HiddenSectors: .int 0
.globl start;
                               LargeSectors: .int 0
                               DriveNo: .short 0
                               Signature: .byte 41 #41 = floppy
start:
jmp .stage1 start
                               VolumeID: .int 0x00000000
                               VolumeLabel: .string "myOS"
OEMLabel: .string "BOOT"
                               FileSystem: .string "FAT12"
BytesPerSector: .short 512
SectorsPerCluster: .byte 1
                                .stage1 start:
ReservedForBoot: .short 1
                                   cli # Not safe here!
NumberOfFats: .byte 2
                                   xorw %ax, %ax # Segment zero
RootDirEntries: .short 224
                                   movw %ax, %ds
Logical Sectors: .short 2880
                                   movw %ax, %es
                                                 What about CS?
MediumByte: .byte 0x0F0
                                   movw %ax, %ss
SectorsPerFat: .short 9
SectorsPerTrack: .short 18
```



### The Stage 1 Bootloader must...

- Enable address A20
- Switch to 32-bit protected mode
- Setup a stack
- Load the kernel
  - Yet, the kernel is on disk: how to navigate the file system? There is not much space for code...
  - Load the Stage 2 bootloader!



#### A20 Enable

- Intel 80286 increased the addressable memory to 16 Mb (24 address lines)
- How to keep backward compatibility with 8086?
  - "wrap-around" problem
  - By default address line 20 is forced to zero!
- How to enable/disable this line?
  - Use the 8042 keyboard controller (sic!)
  - It had a spare pin which they decided to route the A20 line through





#### A20 Enable

- The output port of the keyboard controller has a number of functions.
- Bit 1 is used to control A20:
  - -1 = enabled
  - -0 = disabled
- Port 0x64 is used to "communicate" an operation to the controller
  - 0xd1 means "write"
- 0xdd and 0xdf enable/disable A20, when sent to port 0x60
  - You have to wait for previous operations to complete (the controller is slow)





#### A20 Enable

```
call wait for 8042
 movb $0xd1, %al #command write
  outb %al, $0x64
  call wait for 8042
 movb $0xdf, %al # Enable A20
  outb %al, $0x60
  call wait for 8042
wait for 8042:
  inb %al, $0x64
  tesb $2, %al # Bit 2 set = busy
  jnz wait for 8042
  ret
```




#### x86 Protected Mode

- This execution mode was introduced in 80286 (1982)
- With 80386 (1985) it was extended by adding paging
- CPUs start in Real Mode for backwards compatibility
- Still today, x86 Protected Mode must be activated during system startup



### x86\_64 Registers





# x86\_64 Registers

ZMMO	YMM0	XMM0	ZMM1	YMM1 [	XMM1	ST(0)	MM0	ST(1)	MM1	AH AL A	EAX RAX	R8 [888	R8D R12	2 R128 R12D	CR0	CR4	
ZMM2	YMM2	XMM2	ZMM3	YMM3	XMM3	ST(2)	MM2	ST(3)	MM3	вн в. в.	GEBX RBX	R9	R9D R13	3 R13W R13D	CR1	CR5	
ZMM4	YMM4	XMM4	ZMM5	YMM5	XMM5	ST(4)	MM4	ST(5)	MM5	CH (C) (C)	ECX RCX	R10	R10D R14	4 [R148 R14D]	CR2	CR6	
ZMM6	YMM6	XMM6	ZMM7	YMM7	XMM7	ST(6)	MM6	ST(7)	MM7	DH DL D	EDX RDX	R11	R11D R1	5 R158 R15W R15D	CR3	CR7	
ZMM8	YMM8	XMM8	ZMM9	YMM9	XMM9					ВР	EBP RBP	DI EDI F	RDI	ESP RIP	CR3	CR8	
ZMM1	.0 YMM10	XMM10	ZMM11	YMM11	XMM11	CW	FP_IP	FP_DP	FP_CS	SI	esi RSI	SP ESP F	RSP		MSW	CR9	
ZMM1	.2 YMM12	XMM12	ZMM13	YMM13	XMM13	SW		_				_		_		CR10	)
ZMM1	.4 YMM14	XMM14	ZMM15	YMM15	XMM15	TW			_		bit Register			16-bit Regi		CR11	_
ZMM16	ZMM17 ZMM1	8 ZMM19	ZMM20 ZN	MM21 ZMM22	ZMM23	FP_DS		312-0	it Register	120	s-bit Registe	32-011	Register	o-bit Regi	Ster	CR12	2
ZMM24	ZMM25 ZMM2	6 ZMM27	ZMM28 ZN	MM29 ZMM30	ZMM31	FP_OPC	FP_DP	FP_IP	C	SS	S DS	GDTR	IDTR	DR0	DR6	CR13	3
									ES	S F	S GS	TR	LDTR	DR1	DR7	CR14	ŀ
												RFLAGS	EFLAGS FLAGS	DR2	DR8	CR15	MXCSR
												27103		DR3	DR9		
														DR4	DR10	DR12	DR14
														DR5	DR11	DR13	DR15





## CR0

Bit	Name	Full Name	Description							
0	PE	Protected Mode Enable	If 1, system is in protected mode, else system is in real mode							
1	MP	Monitor co-processor	Controls interaction of WAIT/FWAIT instructions with TS flag in CR0							
2	EM	Emulation	If set, no x87 FPU is present, if clear, x87 FPU is present							
3	TS	Task switched	Allows saving x87 task context upon a task switch only after x87 instruction used							
4	ET	Extension type	On the 386, it allowed to specify whether the external math coprocessor was an 80287 or 80387							
5	NE	Numeric error	Enable internal x87 floating point error reporting when set, else enables PC style x87 error detection							
16	WP	Write protect	When set, the CPU can't write to read-only pages when privilege level is 0							
18	AM	Alignment mask	Alignment check enabled if AM set, AC flag (in EFLAGS register) set, and privilege level is 3							
29	NW	Not-write through	Globally enables/disable write-through caching							
30	CD	Cache disable	Globally enables/disable the memory cache							
31	PG	Paging	If 1, enable paging and use the CR3 register, else disable paging							





## **Entering Basic Protected Mode**

- The code must set bit 0 (PE) of register CR0
- Setting PE to 1 does not immediately activate all its facilities
- It happens when the CS register is first updated
- This can be only done using a far jump (ljmp) instruction, as already mentioned.
- After this, code executes in 32/64-bit mode





#### **Entering Basic Protected Mode**

```
ljmp 0x0000, PE mode
 .code32
PE mode:
 # Set up the protected-mode data segment registers
movw $PROT MODE DSEG, %ax
movw %ax, %ds
movw %ax, %es
movw %ax, %fs
movw %ax, %qs
```



movw %ax, %ss


#### Segment Registers in Protected Mode

- In Protected Mode, a segment is no longer a raw number
- It contains (also) an index into a table of segment descriptors
- There are three types of segments:
  - code
  - data
  - system





#### Descriptor Table Entry




- Base: 32-bit linear addressing pointing to the beginning of the segment
- **Limit**: size of the segment
- **G**: *Granularity*. If set, size is to be multiplied by 4096
- **Descriptor Privilege Level** (DPL): a number in [0-3] to control access to the segment





#### Protected Mode: Privilege Levels



Ring 3 has restricted access to memory management, instructions execution (around 15 allowed only at ring 0), and I/O ports






#### Descriptor Tables

- Two tables are available on x86 architectures
- Global Descriptor Table (GDT):
  - This is a system-wide table of descriptors
  - It is pointed by the GDTR register
- Local Descriptor Table (LDT):
  - Pointed by the LDTR register
  - Not used anymore






#### Segment Selectors



- **TI**: set to 0 for the GDT, set to 1 for the LDT
- Index: specifies the segment selector within the associated table
- Requested Privilege Level (RPL): we'll come to that later




# Segmented Addressing Resolution







# Segmented Addressing Resolution








# Segment Caching

- Accessing the GDT for every memory access is not performance-wise
- Segment registers have a non-programmable hidden part to store the cached descriptor








# x86 Enforcing Protection

- A Descriptor Entry has a DPL
- The firmware must check if an access to a certain segment is allowed
- There must be a way to change current privilege








# Data Segment vs Code Segment

- RPL is present only in data segment selectors (e.g. SS or DS)
- Current Privilege Level
   (CPL): this is only in CS,
   which can be loaded only
   with a limp/lcall



Overall we have 3 different privilege-level fields:
 CPL, RPL, and DPL





# Protection upon Segment Load


• CPL is managed by the CPU: it's *always* equals to the current CPU privilege level

- CPU Memory protection comes at two points:
  - Memory access via a linear address
  - Data segment selector load operation





# Protection upon Segment Load







# Getting Higher Privileges

- Accessing segment with a higher privilege (lower ring) with not control might allow malicious code to subvert the kernel
- To control transfer, code must pass through a controlled gate

• **Gate descriptors** are used to identify possible gates through which control can pass






# Controlled Access Through Gates

Kernel Space (Ring 0)

User Space (Ring 3)



Non-admitted cross-segment jump





#### Gate Descriptors

- A gate descriptor is a segment descriptor of type system:
  - Call-gate descriptors
  - Interrupt-gate descriptors
  - Trap-gate descriptors
  - Task-gate descriptors
- These are referenced by the Interrupt
   Descriptor Table (IDT), pointed by the IDTR register






#### Interrupts vs Traps

- Interrupts are **asynchronous events** not related to the current CPU execution flow
- Interrupts are generated by external devices, and can be masked or not (NMI)
- Traps (or *exceptions*) are **synchronous events**, strictly related to the current CPU execution (e.g. division by zero)
- Traps are the historical way to demand access to kernel mode





#### IDT and GDT Relations





#### GDT in Linux

Linux's GDT	Segment Selectors	Linux's GDT	Segment Selectors
null	0x0	TSS	ox80 ← Different for all cores
reserved		LDT	ox88 ← Shared across all cores
reserved		PNPBIOS 32-bit code	0x90
reserved		PNPBIOS 16-bit code	0x98
not used		PNPBIOS 16-bit data	0xa0
not used		PNPBIOS 16-bit data	0xa8
TLS #1	0x33	PNPBIOS 16-bit data	0xb0
TLS #2	0x3b	APMBIOS 32-bit code	0xb8
TLS #3	0x43	APMBIOS 16-bit code	0xc0
reserved		APMBIOS data	0xc8
reserved		not used	
reserved		not used	
kernel code	0x60 (KERNEL_CS)	not used	
kernel data	Ox68 (_KERNEL_DS)	not used	
user code	0x73 (_USER_CS)	not used	1
user data	Ox7b (USER_DS)	double fault TSS	0xf8

There is one copy of this table for each core





- Its an x86 structure holding information about a task
- It is intended to handle task management
- It stores:
  - Processor registers state
  - I/O Port Permissions
  - Inner-level Stack Pointers
  - Previous TSS link






- It can be everywhere in memory (hence the GDT entry required to access it)
- On Linux, it's in kernel data memory
- Each TSS is stored in the int\_tss array.
- The selector is kept in the Task Register (TR)
- It can be loaded using the privileged ltr instruction












- The *Base* field within the *n*-th core TSS register points to the *n*-th entry of the int\_tss array
- G=0 and Limit=0xeb
  - given that TSS is 236 bytes in size
- *DPL*=0
  - •TSS cannot be accessed in user mode





# Entering Ring 0 from Ring 3







# Protected Mode Paging

 Since 80386, x86 CPUs add an additional step in address translation

**Memory Address Translation** x86 CPU with segmentation and paging Assembly **Physical** Logical Linear Northbridge Segmentation **Paging** Instructions **Address Address Address** Unit Chip Unit in Program





RAM Modules

# Protected Mode Paging


- Paging has to be explicitly enabled
  - Entering Protected Mode does not enable it automatically
  - Several data structures must be setup before

 Paging allows to manage memory protection at a smaller granularity than segmentation





# i386 Paging Scheme





# i386 Paging Scheme

- Both levels entail 4 KB memory blocks
- Each block is an array of 4-byte entries
- Hence we can map 1 K x 1K pages
- Since each page is 4 KB in sixe, we get a 4 GB virtual addressing space



#### i386 PDE entries

#### Page-Directory Entry (4-KByte Page Table)

31		12	11	9	8	7	6	5	4	3	2	1	0
	Page-Table Base Address		Ava	ail	G	ъ о В	0	А	PCD	P W T	U / S	R / W	Р
	Available for system programmer's use Global page (Ignored) ————————————————————————————————————												





#### i386 PTE entries

#### Page-Table Entry (4-KByte Page)


31	12	11	9	8	7	6	5	4	3	2	1	0
Page Base Address		Avai		O	P A T	D	Α	PCD	P W T	U / S	R / W	Р
Available for system programmer's use Global Page (TLB caching policy) ————————————————————————————————————												






#### Translation Lookaside Buffer

**Memory Address Translation** 





#### Translation Lookaside Buffer








#### Relations to Trap/Interrupt Table

- Upon a TLB miss, firmware accesses the page table
- The first checked bit is PRESENT
- If this bit is zero, a page fault occurs which gives rise to a trap
- CPU registers (including EIP and CS) are saved on the system stack
- They will be restored when returning from trap: the trapped instruction is re-executed
- Re-execution might give rise to additional traps, depending on firmware checks on the page table
- As an example, the attempt to access a read only page in write mode will give rise to a trap (which triggers the **segmentation fault** handler)





## Linux memory layout on i386








#### Physical Address Extension (PAE)

- An attempt to extend over the 4GB limit on i386 systems
- Present since the Intel Pentium Pro
- Supported on Linux since kernel 2.6
- Addressing is extended to 36 bits
- This allows to drive up to 64 GB of RAM memory
- Paging uses 3 levels
- CR4.PAE-bit (bit 5) tells if PAE is enabled





### Physical Address Extension (PAE)







## x64 Paging Scheme


- PAE is extended via the so called "long addressing"
- 2<sup>64</sup> bytes of logical memory in theory
- Bits [49-63] are short-circuited to 1
  - Up to 248 canonical form addresses (lower and upper half)
  - A total of 256 TB addressable memory
- Linux currently allows for 128 TB of logical addressing of individual processes and 64 TB for physical addressing





#### Canonical Addresses

64-bit




**48-bit** 






## Linux memory layout on x64







## 48-bit Page Table (4KB pages)





## CR3 and Paging Structure Entries

6 6 6 6 5 5 5 5 5 5 5 5 5 5 5 5 5 5 5 5									
Reserved <sup>2</sup>			Address of PML4 table			Ignored	P P C W Iq D T	n.	CR3
D 3	Ignored	Rsvd.	Address of page-directory-pointer table Ig				PPUI g A C W/S	1	PML4E: present
Ignored								0	PML4E: not present
X D	Ignored	Rsvd.	Address of 1GB page frame Reserved T			Ign. G <u>1</u> I	D A C W/S	1	PDPTE: 1GB page
X D	Ignored	Rsvd.	Address of page directory Ign. 0   PPU R C W/S w					\\ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \	PDPTE: page directory
Ignored									PDTPE: not present
X D	Ignored	Rsvd.	Address of 2MB page frame	Reserve	ed P	Ign. G <u>1</u> I	DIT	-	PDE: 2MB page
X D	Ignored	Rsvd.	Address of page table Ign. D I A C W / N D T / S W					<sup>2</sup> / <sub>√</sub> 1	PDE: page table
Ignored								0	PDE: not present
X D	Ignored	Rsvd.	Address of 4KB page frame Ign. G P D A C W J / S W					? √ <u>1</u>	PTE: 4KB page
Ignored								0	PTE: not present





## Huge Pages

- Ideally x64 processors support them starting from PDPT
- Linux typically offers the support for huge pages pointed by the PDE (page size 512\*4KB)
- See: /proc/meminfo and  $/proc/sys/vm/nr_hugepages$
- These can be mmap'ed via file descriptors and/or mmap parameters (e.g. MAP\_HUGETLB flag)
- They can also be requested via the madvise (void \*, size\_t, int) system call (with MADV\_HUGEPAGE flag)





## Back to the bootstrap

- We have enabled Protected Mode
- Addressing mode is still using segmentation
- We can address up to 16 Mb of RAM
- Paging is not yet setup

It's time to start loading the actual kernel



## **Boot Sequence**

**BIOS/UEFI** 

The actual Hardware Startup

Bootloader Stage 1

Executes the Stage 2 bootloader (skipped in case of UEFI)

Bootloader Stage 2

Loads and starts the Kernel

Kernel Startup

The Kernel takes control of and initializes the machine (machine–dependent operations)

Init

First process: basic environment initialization (e.g., SystemV Init, systemd)

Runlevels/Targets

Initializes the user environment (e.g., single-user mode, multiuser, graphical, ...)





## Second Stage Bootloader

- There are various versions of this software
  - In GRUB it is GRUB Stage 2
  - In Win NT it is c:\ntldr
- The second stage bootloader reads a configuration file, e.g. to startup a boot selection menu
  - grub.conf in GRUB, boot.ini in Win NT
- The kernel initial image is loaded in memory using BIOS disk I/O services
  - For Linux, it is /boot/vmlinuz-\*
  - For Win NT, it is c:\Windows\System32\ntoskrnl.exe





#### Historical Linux Bootcode

- The historical bootsector code for LINUX (i386) is in arch/i386/bootsect.s (no longer used)
- It loaded arch/i386/bootsetup.s and the kernel image in memory
- The code in arch/i386/bootsetup.s initialized the architecture (e.g. the CPU state for the actual kernel boot)
- It ultimately gave control to the initial kernel image



# Unified Extensible Firmware Interface (UEFI)

- Modular (you can extend it with drivers)
- Runs on various platforms
- It's written in C
- It supports a bytecode (portability to other architectures)

• It's completely different from BIOS





#### **UEFI** Boot

- UEFI boot manager takes control right after the system is powered on
- It looks at the boot configuration
- It loads the firmware settings into RAM from nvRAM
- Startup files are stored on a dedicated EFI System Partition (ESP)
  - It'a a FAT32 partition
  - It has one folder for each OS on the system
- MBR cannot handle disks larger than 2TB






#### **UEFI** Boot

- It can automatically detect new uefi-boot targets
  - UEFI uses standard path names
    - /efi/boot/boot x64.efi
    - /efi/boot/bootaa64.efi
- UEFI programs can be easily written





#### **GUID Partition Table**





#### Secure Boot

- There is a kind of malware which takes control of the system before the OS starts
  - MBR RootKits
- Usually, these RootKits hijack the IDT for I/O operations, to execute their own wrapper
- When the kernel is being loaded, the RootKit notices that and patches the binary code while loading it into RAM



#### Secure Boot

- UEFI allows to load only signed executables
- Keys to verify signatures are installed in UEFI configuration
  - Platform Keys (PK): tells who "owns and controls" the hardware platform
  - Key-Exchange Keys (KEK): shows who is allowed to update the hardware platform
  - Signature Database Keys (DB): show who is allowed to boot the platform in secure mode



## Dealing with multicores

- Who shall execute the startup code?
- For legacy reasons, the code is purely sequential
- Only one CPU core (the master) should run the code

- At startup, only one core is active, the others are in an idle state
- The startup procedure has to wake up other cores before starting the actual kernel






## Interrupts on Multicore Architectures

- The Advanced Programmable Interrupt Controller (APIC) is used for sophisticated interrupt sending/redirection
- Each core has a Local APIC (LAPIC) controller, which can send Inter-Processor Interrupts (IPIs)
  - LAPICs are connected through the (logical) "APIC Bus"
  - LINT 0 : normal interrupts LINT 1 : Non-maskable Interrupts
- I/O APICs contain a redirection table, which is used to route the interrupts it receives from peripheral buses to one or more local APICs





### LAPIC







## Interrupt Control Register

- The ICR register is used to initiate an IPI
- Values written into it specify the type of interrupt to be sent, and the target core


ICR (upper 32-bits)



The Destination Field (8-bits) can be used to specify which processor (or group of processors) will receive the message

Memory-Mapped Register-Address: 0xFEE00310

#### ICR (lower 32-bits)







## Broadcast INIT-SIPI-SIPI Sequence

```
# address Local-APIC via register FS
                  $sel fs, %ax
    mov
                  %ax, %fs
    mov
# broadcast 'INIT' IPI to 'all-except-self'
          $0x000C4500, %eax; 11 00 0 1 0 0 0 101 00000000
    mov
    mov %eax, %fs:(0xFEE00300)
.BO: btl
                  $12, %fs:(0xFEE00300)
    iс
         .B0
# broadcast 'Startup' IPI to 'all-except-self'
# using vector 0x11 to specify entry-point
# at real memory-address 0x00011000
              $0x000C4611, %eax; 11 00 0 0 1 0 0 0 110 00010001
    mov
    mov %eax, %fs:(0xFEE00300)
               $12, %fs:(0xFEE00300)
.B1: btl
    ic .B1
```

