

Ərk Plugin

Development Guide

Version 0.510











3 3
- ว
_
4
4
4
4
5
5
5
5
5
5
6
6
6
6
7
7
7
8
8
8
8
8
9
9
0
1
2
2
2
2
3

fetch(id=String)	13
fetchAll()	
The IRC object	
send(data=String)	
<pre>privmsg(target=String, message=String, display=True)</pre>	
notice(target=String, message=String, display=True)	
action(target=String,message=String,display=True)	
join(channel=String,key=None)	
part(channel=String,message=None)	
server()	
port()	
nickname()	
id()	
Example plugins	19
Echo	. •
Using HEAP, textWindow(), and handle_input	
osing riezi, textivinaow(), and nandie_input	20

Ərk Plugins

An Θ rk plugin consists of a Python module containing a class, which contains one or more callable methods; the class inherits from a class that comes with Θ rk, **Plugin**.

Installing plugins

To install an Θ rk plugin, copy it into the **plugins** directory in Θ rk's installation directory. Θ rk plugins follow the same rules that Python modules do, and can be contained in directories, span multiple files, etc.

Plugin implementation

All plugins must import the **Plugin** class, which can be imported from the **erk** module. Other objects which make writing plugins easier can also be imported:

- **ERK** An object for displaying and retrieving information from the Θ rk IRC client.
- IRC An object for interacting with IRC servers.
- **HEAP** A shared dict that all plugins have access to.
- Message An enum defining different message types.
- **Event** An enum defining different event types.

All of these, along with the Plugin class, can be imported with **from erk import** *.

The Message enum

This is used by Θ rk to categorize the four types of messages:

1	Message.PUBLIC	Public messages sent to an IRC channel.
2	Message.PRIVATE	Private messages sent to the Ərk IRC client.
3	Message.ACTION	CTCP action messages sent either to a channel or directly to the client.
4	Message.NOTICE	Notice messages sent either to a channel or directly to the client.

Table 1: Message types

The Event enum

This is used by Θ rk to categorize the fifteen types of events that will be passed to plugins:

1	Event.LINE_IN	Triggered whenever a message is sent to the IRC server.
2	Event.LINE_OUT	Triggered whenever a message is received from the IRC server.
3	Event.CONNECT	Triggered when Ərk connects to an IRC server.
4	Event.DISCONNECT	Triggered when Ərk disconnects from an IRC server.
5	Event.REGISTERED	Triggered when Ərk has finished registering with an IRC server.
6	Event.MOTD	Triggered when Ərk receives an IRC server's message of the day.
7	Event.NICK	Triggered when a user changes their nickname.
8	Event.PART	Triggered when a user leaves a channel.
9	Event.JOIN	Triggered when a user joins a channel.
10	Event.KICK	Triggered when a user is kicked from a channel.
11	Event.TOPIC	Triggered when a channel's topic changes.
12	Event.MODE	Triggered when a user or channel mode is set.
13	Event.INVITE	Triggered when Ərk is invited to an IRC channel.
14	Event.QUIT	Triggered when a user quits IRC.
15	Event.ERROR	Triggered when an error is received.
16	Event.TICK	Triggered once a second.

Table 2: **Event** types

The Plugin class

This is the base class of all Ork plugins.

Attributes

The **Plugin** class features three class attributes: **name**, **version**, and **author**. These are set, by default, to "**No name**", "**1.0**", and "**Unknown**", respectively. The values for these attributes are used to display plugin information in the Θ rk client. They should be set to appropriate values in the plugin's __init__ constructor.

There are two more class attributes that can optionally be set: website and source. Both of these attributes are set to None by default. Set website to a URL string to be displayed in the Θ rk client as the plugin's website. Set source to a URL string to be displayed in the Θ rk client as a link to the plugin's source code. These attributes, if desired, should also be set in the plugin's init constructor.

Plugins can be displayed in the Θ rk client with a custom icon; if no icon accompanies the plugin, a default one will be used. Icons should be in the portable network graphic format (PNG), and be placed in the same location the plugin file is. The icon's file name should be the same as the file name of the plugin, with the icon's file extension changed to ".png". So, the icon for a plugin with the filename of MyPlugin.py should be named MyPlugin.png.

To be displayed properly, the plugin's icon should have a width and height of 25 pixels.

Methods

Plugins can contain (but don't have to contain) one or more callable methods.

load()

This method is called when Θ rk first loads the plugin. If the plugin has been disabled via the Θ rk Θ II, this method will be called when the plugin is re-enabled.

unload()

This method is called when Θ rk is shutting down. If the plugin is disabled via the Θ rk Θ rk, this method will be called when the plugin is disabled.

handle_input(text)

This method is called whenever text is entered into the ∂rk client and return is pressed. **text** is an **INPUT()** object. If any plugin's **handle_input()** method returns **True** (or a value that Python would consider **True**), ∂rk will stop processing the input text as soon as the plugins finish execution; this allows plugins to implement their own commands. If used improperly, this can prevent ∂rk from functioning.

For example, if a plugin with the following source code is loaded:

```
from erk import *
class BreakTheClient(Plugin):
   def handle_input(self,text):
     return True
```

This will break user input. Any time a user enters text into the client, the plugin will stop all text processing as soon as the text is entered; Ork will not send any entered text as messages.

The handle_input() method should only return True if no further text processing is desired.

The INPUT() object

```
INPUT(text=String,window=String,console=Boolean)
```

text is a string containing the text that was entered into the client. window is the name of the window the user entered the text into (this will be either a channel or user name, or a server hostname). console will be set to True if the text was entered into a server console window, or False if the text was entered into a channel or user window.

```
# Print if the input came from a console window
if text.console:
   print("The input came from " + text.window + "'s console")

# Print the input
print(text.text)
```

Table 3: Example usage of an INPUT() object

If used as a str(), INPUT() will return .text.

```
input_text = INPUT("hello world","#channel",False)
# Prints "hello world" to the console
print(input_text)
```

Table 4: Using an INPUT() object as a str()

handle_message(msg)

This method is called whenever the Θ rk IRC client receives a PRIVMSG or NOTICE from an IRC server. msg is a PRIVMSG() object.

The PRIVMSG() object

PRIVMSG(type=Message, target=String, sender=String, message=String)

type is a Message object containing the type of message (see <u>The Message enum</u> on page 4). target is the entity the message was sent to (either a channel name, for public messages, or the nickname the Ork client is using for private messages). sender is information about the user that sent the message; this is a string that takes the form <code>nickname!username@host.server</code> contains the IP or hostname of the server the message came from, and <code>port</code> contains the server port the client is connected to.

A **PRIVMSG()** object can be accessed like a normal Python object with four attributes (.type, .target, .sender, and .message):

```
# Print the message sender and contents
print(PRIVMSG.sender + ": " + PRIVMSG.message)

# Print where the message was sent to
print(PRIVMSG.target)

# Print "hello world!" if the message is a public messages
if(PRIVMSG.type == Message.PUBLIC):
    print("hello world!")
```

Table 5: Example usage of a PRIVMSG() object

If used as a str(), a PRIVMSG() object will return .message:

```
msg = PRIVMSG(Message.PUBLIC, "#channel", "bob!bob@host.com", "Hello!")
# This will print "Hello!" to the console
print(str(msg))
```

Table 6: Using a PRIVMSG() object as a str()

If used in a comparison operation, PRIVMSG() will use .type as its value:

```
# Display whether a given PRIVMSG() represents a public messages
if msg == Message.PUBLIC:
    print("It's a public message!")
else:
    print("It's not a public message!")
```

Table 7: Using PRIVMSG() in comparison operations

handle event(event)

This method is called whenever the Θ rk IRC client triggers an event; events occur when certain messages are received from the IRC server. **event** is an **EVENT()** object.

The EVENT() object

```
EVENT(type=Event,data=Dict)
```

type is an **Event** object containing the type of event (see <u>The Event enum</u> on page 4). **data** is a dict that contains different information depending on the type of event.

An **EVENT()** object can be accessed as a normal Python object with two attributes (**.type** and **.data**):

```
# Display if the event is a connection event
if EVENT.type==Event.CONNECT: print("It's a connection event!")
# Display the contents of the .data attribute
for key in EVENT.data:
    print(EVENT.data[key])
```

Table 8: Example usage of an EVENT() object

If used like a dict(), an EVENT() object will behave like a dict():

```
event = EVENT(Event.LINE_IN, { data: "PING :888CC663" })

# Prints "PING :888CC663"
if "data" in event:
    print(event["data"])
```

Table 9: Using an EVENT() object as a dict()

If used in a comparison operation, **EVENT()** will use .type as its value:

```
# Display whether a given EVENT() represents a connection event
if event == Event.CONNECT:
    print("It's a connection event!")
else:
    print("It's not a connection event!")
```

Table 10: Using EVENT() in comparison operations

EVENT() object contents

Each different **Event** type will have different pass different data to the emitted **EVENT()** object. This data is stored in the **EVENT()**'s .data dict. All values, unless otherwise noted, are **Strings**.

Event	Trigger		.data keys	
LINE_IN	A message is received from the IRC server	line	The line of data sent to the client from the server.	
LINE_OUT	A message is sent to the IRC server	line	The line of data sent to the server from the client.	
CONNECT	Connection to an IRC server	server	The IP or hostname of the server Ərk connected to.	
CONNECT		port	Integer. The port number Θ rk is connected to on the server.	
DISCONNECT	Disconnection from an IRC server	reason	A string describing what caused the disconnection.	
REGISTERED	Server registration completed	nickname	The Ərk client nickname.	
MOTD	Receipt of server's message of the day	motd	List. All lines in the server's MOTD.	
NTCK	NICK User changes their nickname	old	The nickname the client was using prior to the change.	
		new	The user's new nickname.	
PART	User leaves a	user	The user who left the channel.	
	channel	channel	The channel the user left.	
JOTN	JOIN User joins a channel	user	The user who joined the channel.	
JOIN		channel	The channel the user joined.	
			kicker	The user who initiated the channel kick.
KICK	User is kicked from a channel	target	The user being kicked.	
		channel	The channel the kick occurred in.	
		message	The reason for the kick, if any.	

Event	Trigger	.data keys	
	User sets a channel topic	user	The user who set the channel topic.
TOPIC		channel	The channel whose topic was topic was set.
		topic	The new channel topic.
	User sets a channel or user mode	user	The user who set or unset the mode.
		target	The user (or channel) the mode is being applied to.
MODE		set	Boolean. Set to True if the user is setting a mode, or False if the user is un-setting a mode.
		modes	The mode(s) being set or unset by the user.
		arguments	List. Any arguments passed along with the mode.
	Channel invitation is received from a user	user	The user that sent the channel invitation.
INVITE		target	Who the channel invitation was sent to.
		channel	The name of the channel the client is being invited to.
OUTT	User quits IRC	user	The user quitting IRC.
QUIT		message	The user's parting message, if any.
ERROR	Server sends an error message	message	The error message sent by the server.
ТІСК	Triggered once a second	uptime	Integer. How long the Ərk client has been running, in seconds.

The HEAP object

The **HEAP** object is a shared dict that all plugins have access to. This allows for limited cross-plugin communication and the potential for data persistence. When Θ rk starts up, **HEAP** is created as an empty dict (**HEAP** = {}). Other than creating **HEAP**, the Θ rk application has no interactions with **HEAP**; it is designed to be used by plugins *only*.

The ERK object

The **ERK** object is an interface for the Θ rk GUI. It can be used to display text in the client. It's a singleton object that every plugin can access, and features XX methods.

active(message=String,log=False)

```
# Prints "Hello, world!" to the current active window
ERK.active("Hello, world!")

# Prints "Hello, world!" and makes sure it is written to the log
ERK.active("Hello, world!", True)
```

The active() method prints text to the current active window in the Θ rk client; it prints nothing if there is no active window. message is the text to display; log sets whether the printed text is to be written to Θ rk's log. log is set to False by default. Text that is not logged will not be saved when Θ rk writes channel/private message logs.

console(message=String, log=False)

```
# Prints "Hello, world!" to the console
ERK.console("Hello, world!")

# Prints "Hello, world!" and makes sure it is written to the log
ERK.console("Hello, world!", True)
```

The **console()** method prints text to the current server console. **message** is the text to display; **log** sets whether the printed text is to be written to Θ rk's log. **log** is set to **False** by default. Text that is not logged will not be saved when Θ rk writes console logs.

channel(name=String, message=String, log=False)

```
# Prints "Hello, world!" to the chat window for #erk
ERK.channel("#erk","Hello, world!")

# Prints "Hello, world!" and makes sure it is written to the log
ERK.channel("#erk","Hello, world!",True)
```

The **channel()** method prints text to a specific channel or user chat window. **name** is the name of the channel or user window to print to, **message** is the text to display, and **log** sets whether the printed text is to be saved to Θ rk's log. **log** is set to **False** by default. Text that is not logged will not be saved when Θ rk writes channel logs.

textWindow(title=String,contents=String)

```
# Displays "Hello world!" in a window
ERK.textWindow("Greeting","Hello world!")

# Create a text window
window = ERK.textWindow("Text Window")

# Write text to the new text window
window.write("Hello, world!")

# Get text window contents
print(window.contents())

# Clear text window
window.clear()
```

The **textWindow()** method creates a window in Θ rk and displays text on it. The method will return a window object that can be saved for later use; the window is a **QMainWindow** (a type of Qt widget) with three methods:

- write(String) Writes text to the window
- contents() Returns the text contents of the window
- clear() Clears all text from the window

fetch(id=String)

```
# Get the connection's ID
id = IRC.id()

# Fetch another IRC connection with the id
other_IRC = ERK.fetch(id)

# Print the other connection's nickname
print(other_IRC.nickname())
```

The **fetch()** method takes a connection ID (as returned by the **IRC** object's **id()** method) as an argument and returns an instance of the **IRCConnectionObject** for the server connection with that ID. If the ID is invalid or not found, **fetch()** returns **None**.

fetchAll()

```
# Get all connections
connections = ERK.fetchAll()

# Print each server the client is connected to
for server in connections:
    print(server.server()+":"+str(server.port()))
```

The **fetchAll()** method returns a list of **IRCConnection** objects, one for each IRC server that Θ rk is currently connected to.

The IRC object

The IRC object is an interface for the Θ rk IRC client. If Θ rk is connected to multiple IRC servers, the IRC object works as an interface for the connection that triggered the plugin execution. For example, let's assume that Θ rk is connected to two IRC servers, irc.efnet.org and irc.freenode.net. Below is a plugin that echoes back any private messages sent to it. If a private message is sent to the client from irc.freenode.net, the call to IRC.privmsg() will send the echo message only to the irc.freenode.net connection.

```
from erk import *

class Echo(Plugin):
   def handle_message(self,incoming):
     if incoming==Message.PRIVATE:
        nick = incoming.sender.split('!')[0]
        IRC.privmsg(nick,incoming.message)
```

The IRC object is an instance of the IRCConnectionObject, and internal object used to interact with an IRC server connection maintained by Θ rk. The object will always be set to interact with the server connection that triggered the plugin's execution. Access to other server connections is possible with the ERK object's fetch() and fetchAll() methods.

send(data=String)

```
# Joins a channel named #example
IRC.send("JOIN #example")

# Sends a message to #example
IRC.send("PRIVMSG #example Hello, world!")
```

The **send()** method sends a raw, unaltered message to the IRC server. This allows to use functionality not handled by other **IRC** methods.

privmsg(target=String, message=String, display=True)

```
# Sends a public message to #example
IRC.privmsg("#example","Hello, world!")

# Sends a message to #example without displaying it in the client
IRC.privmsg("#example","Hello, world!",False)
```

The **privmsg()** method sends a chat message to the IRC server. **target** is the recipient of the message (a channel or user name), and **message** is the contents of the message. This message will displayed in Θ rk the same as it would be displayed if sent via the GUI. To prevent the message from being displayed in Θ rk, pass **False** as a third argument to the method.

notice(target=String, message=String, display=True)

```
# Sends a public notice to #example
IRC.notice("#example","Hello, world!")

# Sends a notice to #example without displaying it in the client
IRC.notice("#example","Hello, world!",False)
```

The **notice()** method sends a notice message to the IRC server. **target** is the recipient of the message (a channel or user name), and **message** is the contents of the message. This message will displayed in Θ rk the same as it would be displayed if sent via the GUI. To prevent the message from being displayed in Θ rk, pass **False** as a third argument to the method.

action(target=String, message=String, display=True)

```
# Sends a public CTCP action to #example
IRC.action("#example", "says hello!")

# Sends a CTCP action to #example without displaying it
# in the client
IRC.action("#example", "says hello!", False)
```

The **action()** method sends a CTCP action message to the IRC server. **target** is the recipient of the message (a channel or user name), and **message** is the contents of the message. This message will displayed in Θ rk the same as it would be displayed if sent via the GUI. To prevent the message from being displayed in Θ rk, pass **False** as a third argument to the method.

join(channel=String,key=None)

```
# Joins #example
IRC.join("#example")

# Joins #example with a key
IRC.join("#example", "my_channel_key")
```

The **join()** method causes the IRC client to join a channel. If the channel requires a key to join, pass the channel key as a second argument.

part(channel=String, message=None)

```
# Parts #example
IRC.part("#example")

# Parts #example with a message
IRC.part("#example", "See you later!")
```

The **part()** method causes the IRC client to leave a channel. An optional message can be passed as a second argument to part with a message.

server()

```
# Get the IP/hostname of the IRC server
server = IRC.server()
```

The **server()** method returns the IP or hostname of the IRC server as a string.

port()

```
# Get the port on the IRC server
port = IRC.port()
```

The **port()** method returns the port on the IRC server as an integer.

nickname()

```
# Get the current nickname
nickname = IRC.nickname()
```

The **nickname()** method returns the nickname currently in use as a string.

id()

```
# Get the connection's ID
id = IRC.id()
```

The **id()** method returns the IRC connection's identification token as a string. Each IRC connection has a unique ID which is generated randomly when the connection is created. The ID returned from this method can be used with the **ERK** object's **fetch()** method, allowing access to any connection the Θ rk client is using from any other connection.

Example plugins

Echo

This plugin will cause Θ rk to echo any private message sent to it back to the sender.

```
1 from erk import *
3 class Echo(Plugin):
    def __init__(self):
     self.name = "Echo"
5
     self.version = "1.0"
7
     self.author = "Dan Hetrick"
8
    def handle_message(self,msg):
9
10
11
      # Execute if we're received a private message
12
      if msg==Message.PRIVATE:
13
        # Extract the sender's nickname from msg.sender
14
15
         nickname = msg.sender.split('!')[0]
16
17
         # Send the senders message back to them
18
         IRC.privmsg(nickname, msg.message)
```

Using HEAP, textWindow(), and handle_input

This plugin will collect any private messages the Θ rk client receives (from any connection) and store them in **HEAP**. To view all these messages, a command named "/pm" is created; when entered into the text entry of any window, the collected private messages are displayed in a **textWindow**.

```
1 from erk import *
2
3 class PMLogger(Plugin):
   def init (self):
      self.name = "PM Logger"
6
      self.version = "1.0"
7
     self.author = "Nutjob Labs"
8
     self.display = None
9
10
    def load(self):
11
     # Create a place to store private messages
12
     HEAP["private messages"] = []
13
14
    def unload(self):
15
     # Delete stored private messages
16
      del HEAP["private messages"]
17
18
    def handle message(self, msg):
19
20
      # Store private messages
21
      if msq == Message.PRIVATE:
22
        HEAP["private messages"].append(msg.sender+": "+msg.message)
23
24
    def handle input(self, text):
25
26
      # If the user enters the command...
27
      if text.text == "/pm":
28
29
        # Create the textWindow if it hasn't been created
30
        if self.display:
31
         self.display.clear()
32
        else:
33
          self.display = ERK.textWindow("Private Messages")
34
35
        # Display stored private messages
36
        self.display.write( "\n".join(HEAP["private messages"]) )
37
38
        # Return True so /pm isn't sent as a chat message
39
        return True
40
```