

# **MAGIC Documentation**

Release 5.1

The MAGIC dev team

## CONTENTS

1	Intro	duction	1
	1.1	Foreword	1
	1.2	Giving credit	2
2	Get I	MagIC and run it	3
	2.1	Download the code	3
	2.2	Setting up the environment variables	3
	2.3	Setting up compiler options and compiling	3
	2.4	Preparing a production run	5
3	Form	nulation of the (magneto)-hydrodynamics problem	7
	3.1	The anelastic approximation	7
	3.2	An adiabatic reference state	8
	3.3	MHD equations	10
	3.4	Boundary conditions and treatment of inner core	13
4	Num	erical technique	15
	4.1	Poloidal/toroidal decomposition	15
	4.2	Spherical harmonic representation	16
	4.3	Radial representation	17
	4.4	Spectral equations	18
	4.5	Time-stepping schemes	22
	4.6	Coriolis force and non-linear terms	23
	4.7	Boundary conditions and inner core	23
5	Cont	ributing to the code	27
	5.1	Checking the consistency of the code	27
	5.2	Advices when contributing to the code	28
	5.3	Building the documentation and contributing to it	28
6	Inpu	t parameters	31
	6.1	Grid namelist	32
	6.2	Control namelist	33
	6.3	Physical parameters namelist	36
	6.4	External Magnetic Field Namelist	42
	6.5	Start field namelist	43
	6.6	Output control namelist	46
	6.7	Mantle and Inner Core Namelists	58
7	Inter	ractive communication with the code using signal. TAG	61

8	Outp	ut files	63
	8.1	Log file: log.TAG	64
	8.2	Default time-series outputs	65
	8.3	Additional optional time-series outputs	
	8.4	Time-averaged radial profiles	76
	8.5	Transport properties of the reference state	
	8.6	Nonlinear mapping of the Chebyshev grid	81
	8.7	Spectra	82
	8.8	Graphic files G_#.TAG and G_ave.TAG	86
	8.9	Movie files *_mov.TAG	91
	8.10	Restart files rst_*.TAG	
	8.11	Poloidal and toroidal potentials at given depths	
	8.12	TO outputs	
	8.13	Radial spectra rB[r p]Spec.TAG	
	8.14	Potential files [V B T]pot_#.TAG	
	0.1.	1 otendari mes [ v   2   1   poo_    v 1110   v 1   v	100
9	Data	visualisation and post-processing	107
	9.1	Requirements	107
	9.2	Configuration: magic.cfg file	
	9.3	Python functions and classes	
		•	
<b>10</b>	Desci	ription of the Fortran modules	139
	10.1	Main program magic.f90	139
	10.2	Base modules	140
	10.3	MPI related modules	167
	10.4		
		Pre-calculations	
	10.6	Time stepping	
	10.7	Linear calculation part of the time stepping (LMLoop)	
	10.8	Non-linear part of the time stepping (radial loop)	
		Chebyshev polynomials and cosine transforms	
		Legendre transforms	
		Fourier transforms	
		Linear algebra	
		Radial derivatives and integration	
		· · · · · · · · · · · · · · · · · · ·	
		Blocking and LM mapping	
		IO: graphic files, movie files, coeff files and potential files	
		IO: RMS force balance, torsional oscillations, misc	
		Reading and storing check points (restart files)	
	10.19	Useful additional libraries	349
Fo	rtran ]	Module Index	355
Рy	thon N	Module Index	357
Ind	dev		350

### INTRODUCTION

### 1.1 Foreword

**MagIC** is a numerical code that can simulate fluid dynamics in a spherical shell. MagIC solves for the Navier-Stokes equation including Coriolis force, optionally coupled with an induction equation for Magneto-Hydro Dynamics (MHD) and a temperature (or entropy) equation under both the anelastic and the Boussinesq approximations.

**MagIC** uses Chebyshev polynomials in the radial direction and spherical harmonic decomposition in the azimuthal and latitudinal directions. The time-stepping scheme relies on a semi-implicit Crank-Nicolson for the linear terms of the MHD equations and a Adams-Bashforth scheme for the non-linear terms and the Coriolis force.

**MagIC** is written in Fortran and designed to be used on supercomputing clusters. It thus relies on a hybrid parallelisation scheme using both OpenMP and MPI. Postprocessing functions written in python (requiring matplotlib and scipy) are also provided to allow a useful data analysis.




Fig. 1.1: Mean walltime of the MagIC code on the supercomputer stampede versus number of CPUs for a dynamo model computed at three different numerical resolutions  $(N_{\phi}, N_{\theta}, N_r)$ . The solid black lines show the ideal scalings.

MagIC is a free software. It can be used, modified and redistributed under the terms of the GNU GPL v3 licence.

## 1.2 Giving credit

In case you intend to publish scientific results obtained with the MagIC code or present them in a conference, we (the developers of MagIC) kindly ask to be acknowledged with a reference to the website https://magic-sph.github.io/ or https://github.com/magic-sph/magic.

We also suggest to give appropriate reference to one or several of the following papers:

- Boussinesq equations: Wicht (2002, PEPI, 132, 281-302)
- Anelastic equations: Gastine & Wicht (2012, Icarus, 219, 28-442)
- Boussinesq benchmark: Christensen et al. (2001, PEPI, 128, 25-34)
- Anelastic benchmark: Jones et al. (2011, Icarus, 216, 120-135)

**CHAPTER** 

**TWO** 

### **GET MAGIC AND RUN IT**

### 2.1 Download the code

You can download a snapshot of the code from the Git repository using

```
$ git clone https://github.com/magic-sph/magic.git
```

In case you already have an account on github.com and uploaded a public SSH key on it, you could then rather use SSH:

```
$ git clone ssh://git@github.com/magic-sph/magic.git
```

## 2.2 Setting up the environment variables

Although not mandatory, it is strongly recommended to correctly source the environment variables of the MagIC code. It will ensure a smoother usage of the post-processing *python classes* and allow to run the *auto-test suite*. To do that, just go to the root directory of the MagIC code (magic) and source sourceme file that corresponds to your \$SHELL environment variable.

In case you use bash, ksh or zsh, just use:

```
$ source sourceme.sh
```

In case you use csh or tcsh, rather use

```
$ source sourceme.csh
```

You can make sure that the environment variables have been correctly sourced by typing:

```
$ echo $MAGIC_HOME
$ echo $PYTHONPATH
```

If you don't want to source sourceme.[c]sh on each session, you can add the following into your .bash\_profile (or .profile or .zprofile or .cshrc):

```
$ source whereverYouCheckedOut/magic/sourceme.sh
```

To get started, you then need to compile the code

## 2.3 Setting up compiler options and compiling

Go to the directory where the source files of MagIC are contained

```
$ cd $MAGIC_HOME/src
```

and edit the Makefile there to specify your specific compiler options.

### 2.3.1 Makefile options

#### **Select compiler**

Set a suitable compiler in the first line of the Makefile: COMPILER = <compiler\_phrase>. The options are intel, gnu or amd - depending on your available compilers.

List of default compilers

Compiler Option	Normal	With MPI
intel	ifort, icc	mpiifort, mpiicc
gnu	gfortran, gcc	mpif90, mpicc
amd	openf95	

#### **Select compiling options**

- PRECISION Set it to 'dble' for double-precision calculations or to 'sngl' for single-precision calculations
- OUT\_PREC Set it to 'dble' for double-precision in binary outputs or to 'sngl' for single precision
- PRODRUN Set it to yes for production run, no for debugging.
- USE\_MPI Set to yes to use MPI, set it to no if you want a serial version of the code.
- OPENMP Set it to yes to use the hybrid version of the code, or to no for a pure MPI (or serial) version.
- DEBUG Set to all to enable the full debug flags. While running in debugging mode, set PRODRUN to no.
- USE\_FFTLIB This option lets you select the library you want to use for Fast Fourier Transforms. This can be set to 'JW' or 'MKL'. 'JW' refers to the inbuilt library by **J** ohannes **W** icht, while 'MKL' refers to the Intel Math Kernel Library. Use 'JW' if you don't have Intel MKL installed.
- USE\_MKL Set to yes if you have Intel MKL installed and want to use it for matrix operations.
- USE HDF5 Set to yes if you want the restart file to be written in the HDF5 format

#### **Architecture (Intel compilers only)**

If you're using intel compilers and if your computer is capable of following specific intel instruction sets (sse3 or AVX), then the Makefile automatically should automatically detects and sets  $FFLAG\_ARCH\_OPT = -xsse3$  or  $FFLAG\_ARCH\_OPT = -xAVX$  under intel compiler options.

### MPI INCPATH

This sets the path for your mpi header file mpif.h. The path depends on the computer. For PCs, this is commonly /usr/include or /usr/include/mpi and should be found by the Makefile automatically thanks to the command mpif90 --showme:incdirs. In case this doesn't work, you may need to specify this variable manually in the Makefile. On supercomputing clusters, this variable is in general not used since the mpi.mod file is usually find the standard \$PATH.

### Other compilers

If your available compilers are different from the options provided in the Makefile, then just create a new profile for your desired compiler by changing the options COMP\_FC and COMP\_CC for serial fortran and C compilers and COMP\_MPFC and COMP\_MPCC for compilers with mpi implementation.

## 2.3.2 Compiling the code

Once you've set up your compiling options compile the code using

```
$ make -j
```

The compiler should then produce an executable named magic.exe.

If you want to recompile the code from scratch do

```
$ make clean
```

to remove all the files generated by the compiler.

Once the executable is built, you are now ready to run your first production run!

## 2.4 Preparing a production run

After building the executable, use one of the namelists provided in the \$MAGIC\_HOME/samples directory (called input.nml), adapt it to your physical problem (see *here* for an exhaustive description of the possible options) and run **MagIC** as follows:

• Running a serial version of the code (USE\_MPI=no and OPENMP=no):

```
$ ./magic.exe input.nml
```

• Running the code without OpenMP (USE\_MPI=yes and OPENMP=no) with <n\_mpi> MPI ranks:

```
$ mpiexec -n <n_mpi> ./magic.exe input.nml
```

• Running the hybrid code (USE\_MPI=yes and OPENMP=yes) with <n\_mpi> MPI ranks and <n\_omp> OpenMP threads:

```
$ export OMP_NUM_THREAD = <n_omp>
$ mpiexec -n <n_mpi> ./magic.exe input.nml
```

Note that the  $n_r$  must be a multiple of  $n_p$ , where  $n_r$  is the number of radial grid points (see *here*).

## FORMULATION OF THE (MAGNETO)-HYDRODYNAMICS PROBLEM

The general equations describing thermal convection and dynamo action of a rotating compressible fluid are the starting point from which the Boussinesq or the anelastic approximations are developed. In MagIC, we consider a spherical shell rotating about the vertical z axis with a constant angular velocity  $\Omega$ . The conservation of mass is expressed by the continuity equation:

$$\frac{\partial \rho}{\partial t} + \boldsymbol{\nabla} \cdot \rho \boldsymbol{u} = 0, \tag{3.1}$$

The conservation of momentum by

$$\rho\left(\frac{\partial \boldsymbol{u}}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \,\boldsymbol{u}\right) = -\boldsymbol{\nabla} p + \frac{1}{\mu_0} (\boldsymbol{\nabla} \times \boldsymbol{B}) \times \boldsymbol{B} + \rho \boldsymbol{g} - 2\rho \boldsymbol{\Omega} \times \boldsymbol{u} + \boldsymbol{\nabla} \cdot \boldsymbol{S},\tag{3.2}$$

where S corresponds to the rate-of-strain tensor given by:

$$S_{ij} = 2\nu\rho \left[ e_{ij} - \frac{1}{3}\delta_{ij} \nabla \cdot \boldsymbol{u} \right],$$
  
$$e_{ij} = \frac{1}{2} \left( \frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right).$$

Concerning the energy equation, several forms are possible (using internal energy, temperature or entropy). Here we use entropy s as the main variable, which leads to:

$$\rho T \left( \frac{\partial s}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} s \right) = \boldsymbol{\nabla} \cdot (K \boldsymbol{\nabla} T) + \boldsymbol{\Phi}_{\nu} + \lambda \left( \boldsymbol{\nabla} \times \boldsymbol{B} \right)^{2}, \tag{3.3}$$

where  $\Phi_{\nu}$  corresponds to the viscous heating expressed by

$$\Phi_{\nu} = 2\rho \left[ e_{ij}e_{ji} - \frac{1}{3} \left( \boldsymbol{\nabla} \cdot \boldsymbol{u} \right)^2 \right].$$

Note that we use here the summation convention over the indices i and j. The induction equation is obtained from the Maxwell equations (ignoring displacement current) and Ohm's law (neglecting Hall effect):

$$\frac{\partial \boldsymbol{B}}{\partial t} = \boldsymbol{\nabla} \times (\boldsymbol{u} \times \boldsymbol{B} - \lambda \, \boldsymbol{\nabla} \times \boldsymbol{B}). \tag{3.4}$$

In those equations, the symbols u, B, p and s correspond to velocity, magnetic field, pressure and entropy. g corresponds to gravity and  $\rho$  to density.  $\lambda$  is the magnetic diffusivity,  $\mu_0$  the magnetic permeability,  $\nu$  the kinematic viscosity and K the thermal conductivity.

## 3.1 The anelastic approximation

MagIC relies on the anelastic approximation of the Navier Stokes equations. There are different flavours of this approximation but they all assume that:




Fig. 3.1: Sketch of the spherical shell model and its system of coordinate.

- 1. the departures from the thermodynamic state variables due to convection are small with respect to the reference state.
- 2. the short-period acoustic waves are filtered-out.

This second assumption implies that larger numerical timesteps will be allowed, since the typical timescale of the fast acoustic waves is typically much slower than the convective turnover time. The strict elimination of the acoustic waves formally means

$$\frac{\partial \rho'}{\partial t} = 0$$

in the continuity equation, where  $\rho'$  corresponds here to the density perturbations of the reference state.

The reference state is a background state against which perturbations are described. In MagIC, this background state is assumed to only depends on one spatial variable (radius), but in general it may as well be explicitly time-dependent. Each thermodynamic variable f is then expressed as a sum of a spherically-symmetric time-independent quantity  $\tilde{f}$  and a fluctuating quantity f':

$$f(r,\theta,\phi,t) = \tilde{f}(r) + f'(r,\theta,\phi,t)$$

This separation of variables is then introduced in the set of equations (3.1)-(3.4) to perform a formal **scale analysis**, taking into account that  $f'/\tilde{f} = \epsilon << 1$ . The variables are then expanded in power series of  $\epsilon$  and only the highest order terms are retained.

### 3.2 An adiabatic reference state

In a vigorously convecting astrophysical of geophysical system (like the convecting interior of a planet or a star), the super-adiabaticity of the fluid is extremely small, since the transport of heat by convective motions is highly efficient. Therefore, the reference background state can be assumed to be perfectly adiabatic and obey to the following

equations

$$\frac{d\tilde{T}}{dr} = -\frac{\alpha g\tilde{T}}{c_p},\tag{3.5}$$

where  $c_p$  is the heat capacity and  $\alpha$  is expressed by

$$c_p = T \left( rac{\partial s}{\partial T} 
ight)_p, \quad ext{and} \quad lpha = -rac{1}{
ho} \left( rac{\partial 
ho}{\partial T} 
ight)_p.$$

At this stage, it becomes convenient to start introducing **non-dimensionalised quantities**. The background quantities (density temperature and transport properties) are non-dimensionalised using their values at the spherical shell outer boundary  $r_o$ . The shell thickness  $d = r_o - r_i$  is used as the reference lengthscale. The dimensionless form of Eq. (3.5) then reads:

$$\frac{d\tilde{T}}{dr} = -Di\,\alpha(r)g(r)\tilde{T}(r),\tag{3.6}$$

where  $\tilde{T}$ ,  $\alpha$  and g have been non-dimensionalised using their values at the outer boundary. Di is the dissipation number expressed by

$$Di = \frac{\alpha_o g_o d}{c_p}. (3.7)$$

Di is a measure of the thermal effects due to compressibility, namely viscous and ohmic heating. Di is also the ratio between two length scales: the thickness of the spherical shell d divided by the temperature scale heights  $H_T = -(d \ln T/dr)^{-1}$ .

When  $Di \ll 1$ , the region where convection develops has a nearly constant reference temperature. Since there is no basic temperature stratification, viscous heating (which is the consequence of the thermal stratification due to compressibility) becomes negligible.

**Note:** The Boussinesq limit can thus be recovered by using  $Di \rightarrow 0$ .

Provided an equation of state is given, it is then possible to integrate Eq. (3.6), to obtain the adiabatic background state.

## 3.2.1 Analytical solution in the limit of an ideal gas

In the limit of an ideal gas which follows  $\tilde{p} = \tilde{\rho}\tilde{T}$  and has  $\alpha = 1/\tilde{T}$ , one directly gets:

$$\frac{d\tilde{T}}{dr} = -Di g(r),$$
  
$$\tilde{\rho} = \tilde{T}^{1/(\gamma - 1)},$$

where  $\gamma = c_p/c_v$ . If we now in addition make the assumption of a centrally-condensed mass in the center of the spherical shell of radius  $r \in [r_i, r_o]$ , i.e.  $g \propto 1/r^2$ , this leads to

$$\tilde{T}(r) = Di \frac{r_o^2}{r} + (1 - Di r_o),$$
  

$$\tilde{\rho}(r) = \tilde{T}^m,$$
  

$$Di = \frac{r_i}{r_o} \left( \exp \frac{N_\rho}{m} - 1 \right),$$

where  $N_{\rho} = \ln(\rho_i/\rho_o)$  is the number of density scale heights of the reference state and  $m = 1/(\gamma - 1)$  is the polytropic index.

#### Warning:

- The relationship between  $N_{\rho}$  and the dissipation number Di directly depends on the gravity profile. The formula above is only valid when  $g \propto 1/r^2$ .
- In this formulation, when you change the polytropic index m, you also change the nature of the fluid you're modelling since you accordingly modify  $\gamma = c_p/c_v$ .

## 3.3 MHD equations

One of the assumptions of the anelastic approximation is that the fluctuations due to convection are much smaller than the reference state:

$$\epsilon \simeq \frac{\rho'}{\tilde{\rho}} \simeq \frac{T'}{\tilde{T}} \simeq \frac{p'}{\tilde{p}} \simeq s' \ll 1.$$

In the following, we will treat the equations (3.1)-(3.4) in nondimensional form. There is no unique way to scale the equations and as a consequence different sets of non-dimensional numbers are employed. For convection-driven dynamos, there is four independent control parameters.

We use here the viscous diffusion time  $d^2/\nu_o$  (where  $\nu_o$  is the kinematic viscosity at the outer boundary) as a time unit and  $\nu_o/d$  as the reference velocity. Magnetic field is expressed in units of  $\sqrt{\rho_o\mu_0\lambda_i\Omega}$ , where  $\rho_o$  is the density at the outer boundary and  $\lambda_i$  is the magnetic diffusivity at the **inner** boundary.

**Note:** All the transport properties except the magnetic diffusivity are normalised to their values at the outer boundary. The motivation to rather base the reference magnetic diffusivity to the **inner** boundary is twofold: (i) it allows an easier control of the possible continuous conductivity value in the inner core; (ii) it is a more natural choice when modelling gas giants planets which exhibit a strong electrical conductivity decay in the outer layer.

This leads to the following sets of dimensionless equations:

$$E\left(\frac{\partial \boldsymbol{u}}{\partial t} + \boldsymbol{u} \cdot \nabla \boldsymbol{u}\right) + 2\boldsymbol{e}_{\boldsymbol{z}} \times \boldsymbol{u} = -\nabla \left(\frac{p'}{\tilde{\rho}}\right) + \frac{Ra\,E}{Pr}g(r)\,s'\,\boldsymbol{e}_{\boldsymbol{r}} + \frac{1}{Pm\,\tilde{\rho}}\left(\nabla \times \boldsymbol{B}\right) \times \boldsymbol{B} + \frac{E}{\tilde{\rho}}\nabla \cdot \mathsf{S}, \quad (3.8)$$

$$\nabla \cdot \tilde{\rho} \boldsymbol{u} = 0, \tag{3.9}$$

$$\nabla \cdot \boldsymbol{B} = 0, \tag{3.10}$$

$$\frac{\partial \boldsymbol{B}}{\partial t} = \boldsymbol{\nabla} \times (\boldsymbol{u} \times \boldsymbol{B}) - \frac{1}{Pm} \boldsymbol{\nabla} \times (\lambda(r) \boldsymbol{\nabla} \times \boldsymbol{B}). \tag{3.11}$$

## 3.3.1 Entropy equation and turbulent diffusion

The entropy equation usually requires an additional assumption in most of the existing anelastic approximations. Indeed, if one simply expands Eq. (3.3) with the classical temperature diffusion an operator of the form:

$$\epsilon \, \boldsymbol{\nabla} \cdot (K \boldsymbol{\nabla} T') + \boldsymbol{\nabla} \cdot \left( K \boldsymbol{\nabla} \tilde{T} \right),$$

will remain the right-hand side of the equation. At first glance, there seems to be a  $1/\epsilon$  factor between the first term and the second one, which would suggest to keep only the second term in this expansion. However, for astrophysical

objects which exhibit strong convective driving (and hence large Rayleigh numbers), the diffusion of the adiabatic background is actually very small and may be comparable or even smaller in magnitude than the  $\epsilon$  terms representing the usual convective perturbations. For the Earth core for instance, if one assumes that the typical temperature fluctuations are of the order of 1 mK and the temperature contrast between the inner and outer core is of the order of 1000 K, then  $\epsilon \sim 10^{-6}$ . The ratio of the two terms can thus be estimated as

$$\epsilon \frac{T'/\delta^2}{T/d^2},\tag{3.12}$$

where d is the thickness of the inner core and  $\delta$  is the typical thermal boundary layer thickness. This ratio is exactly one when  $\delta = 1$  m, a plausible value for the Earth inner core.

In numerical simulations however, the over-estimated diffusivities restrict the computational capabilities to much lower Rayleigh numbers. As a consequence, the actual boundary layers in a global DNS will be much thicker and the ratio (3.12) will be much smaller than unity. The second terms will thus effectively acts as a radial-dependent heat source or sink that will drive or hinder convection. This is one of the physical motivation to rather introduce a **turbulent diffusivity** that will be approximated by

$$\kappa \tilde{\rho} \tilde{T} \nabla s$$
,

where  $\kappa$  is the turbulent diffusivity. Entropy diffusion is assumed to dominate over temperature diffusion in turbulent flows.

The choice of the entropy scale to non-dimensionalise Eq. (3.3) also depends on the nature of the boundary conditions: it can be simply the entropy contrast over the layer  $\Delta s$  when the entropy is held constant at both boundaries, or  $d\left(ds/dr\right)$  when flux-based boundary conditions are employed. We will restrict to the first option in the following, but keep in mind that depending on your setup, the entropy reference scale (and thus the Rayleigh number definition) might change.

$$\tilde{\rho}\tilde{T}\left(\frac{\partial s'}{\partial t} + \boldsymbol{u}\cdot\boldsymbol{\nabla}s'\right) = \frac{1}{Pr}\boldsymbol{\nabla}\cdot\left(\kappa(r)\tilde{\rho}\tilde{T}\boldsymbol{\nabla}s'\right) + \frac{Pr\,Di}{Ra}\boldsymbol{\Phi}_{\nu} + \frac{Pr\,Di}{Pm^2\,E\,Ra}\lambda(r)\left(\boldsymbol{\nabla}\times\boldsymbol{B}\right)^2,\tag{3.13}$$

### 3.3.2 The Boussinesg limits of the equation $Di \rightarrow 0$

When the dissipation number  $Di \to 0$  then  $\tilde{T} = \text{cst.}$ . If in addition to that if  $\gamma \neq 1$ , the density background  $\tilde{\rho}$  is also constant.

**Note:** The peculiar configuration of  $\gamma=1$  corresponds to the so-called zero-Grüneisen limit of the Navier-Stokes equation (or isothermal) and is a special case in which Di=0 but a density background (controlled by  $N_{\rho}$ ) is still allowed.

A brief look at Eq. (3.13) then shows than viscous and Ohmic heating will disappear from the entropy equation. Furthermore, temperature and entropy fluctuations become equivalent quantities. If in addition to that we also neglect the possible radial-dependence of the transport properties (electrical conductivity, viscosity and thermal diffusivity), the set of equations (3.8)-(3.13) thus simplifies to the classical Boussinesq set of equations:

$$E\left(\frac{\partial \boldsymbol{u}}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \boldsymbol{u}\right) + 2\boldsymbol{e}_{\boldsymbol{z}} \times \boldsymbol{u} = -\boldsymbol{\nabla} p' + \frac{Ra E}{Pr} g(r) T' \boldsymbol{e}_{\boldsymbol{r}} + \frac{1}{Pm} (\boldsymbol{\nabla} \times \boldsymbol{B}) \times \boldsymbol{B} + E \Delta \boldsymbol{u},$$

$$\boldsymbol{\nabla} \cdot \boldsymbol{u} = 0,$$

$$\boldsymbol{\nabla} \cdot \boldsymbol{B} = 0,$$

$$\frac{\partial \boldsymbol{B}}{\partial t} = \boldsymbol{\nabla} \times (\boldsymbol{u} \times \boldsymbol{B}) + \frac{1}{Pm} \Delta \boldsymbol{B}.$$

$$\frac{\partial T'}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} T' = \frac{1}{Pr} \Delta T'.$$

3.3. MHD equations

### 3.3.3 Dimensionless control parameters

The equations (3.8)-(3.13) are governed by four dimensionless numbers: the Ekman number

$$E = \frac{\nu}{\Omega d^2},\tag{3.14}$$

the Rayleigh number

$$Ra = \frac{\alpha_o g_o T_o d^3 \Delta s}{c_p \kappa_o \nu_o},\tag{3.15}$$

the Prandtl number

$$Pr = \frac{\nu_o}{\kappa_o},\tag{3.16}$$

and the magnetic Prandtl number

$$Pm = \frac{\nu_o}{\lambda_i}. (3.17)$$

In addition to these four numbers, the reference state is controlled by the geometry of the spherical shell given by its radius ratio

$$\eta = \frac{r_i}{r_o},\tag{3.18}$$

and the background density and temperature profiles, either controlled by Di or by  $N_{\rho}$  and m.

#### See also:

In MagIC, those control parameters can be adjusted in the &phys\_param section of the input namelist.

Variants of the non-dimensional equations and control parameters result from different choices for the fundamental scales. For the length scale often  $r_o$  is chosen instead of d. Other natural scales for time are the magnetic or the thermal diffusion time, or the rotation period. There are also different options for scaling the magnetic field strength. The prefactor of two, which is retained in the Coriolis term in (3.8), is often incorporated into the definition of the Ekman number.

### See also:

Those references timescales and lengthscales can be adjusted by several input parameters in the &control section of the input namelist.

### 3.3.4 Usual diagnostic quantities

Characteristic properties of the solution are usually expressed in terms of non-dimensional diagnostic parameters. In the context of the geodynamo for instance, the two most important ones are the magnetic Reynolds number Rm and the Elsasser number  $\Lambda$ . Usually the rms-values of the velocity  $u_{rms}$  and of the magnetic field  $B_{rms}$  inside the spherical shell are taken as characteristic values. The magnetic Reynolds number

$$Rm = \frac{u_{rms}d}{\lambda_i}$$

can be considered as a measure for the flow velocity and describes the ratio of advection of the magnetic field to magnetic diffusion. Other characteristic non-dimensional numbers related to the flow velocity are the (hydrodynamic) Reynolds number

$$Re = \frac{u_{rms}d}{\nu_o},$$

which measures the ratio of inertial forces to viscous forces, and the Rossby number

$$Ro = \frac{u_{rms}}{\Omega d},$$

a measure for the ratio of inertial to Coriolis forces.

$$\Lambda = \frac{B_{rms}^2}{\mu_0 \lambda_i \rho_0 \Omega}$$

measures the ratio of Lorentz to Coriolis forces and is equivalent to the square of the non-dimensional magnetic field strength in the scaling chosen here.

#### See also:

The time-evolution of these diagnostic quantities are stored in the par.TAG file produced during the run of MagIC.

## 3.4 Boundary conditions and treatment of inner core

### 3.4.1 Mechanical conditions

In its simplest form, when modelling the geodynamo, the fluid shell is treated as a container with rigid, impenetrable, and co-rotating walls. This implies that within the rotating frame of reference all velocity components vanish at  $r_o$  and  $r_i$ . In case of modelling the free surface of a gas giant planets or a star, it is preferable to rather replace the condition of zero horizontal velocity by one of vanishing viscous shear stresses (the so-called free-slip condition).

Furthermore, even in case of modelling the liquid iron core of a terrestrial planet, there is no a priori reason why the inner core should necessarily co-rotate with the mantle. Some models for instance allow for differential rotation of the inner core and mantle with respect to the reference frame. The change of rotation rate is determined from the net torque. Viscous, electromagnetic, and torques due to gravitational coupling between density heterogeneities in the mantle and in the inner core contribute.

#### See also:

The mechanical boundary conditions can be adjusted with the parameters *ktopv* and *kbotv* in the &*phys\_param* section of the input namelist.

## 3.4.2 Magnetic boundary conditions and inner core conductivity

When assuming that the fluid shell is surrounded by electrically insulating regions (inner core and external part), the magnetic field inside the fluid shell matches continuously to a potential field in both the exterior and the interior regions. Alternative magnetic boundary conditions (like cancellation of the horizontal component of the field ) are also possible.

Depending on the physical problem you want to model, treating the inner core as an insulator is not realistic either, and it might instead be more appropriate to assume that it has the same electrical conductivity as the fluid shell. In this case, an equation equivalent to (3.11) must be solved for the inner core, where the velocity field simply describes the solid body rotation of the inner core with respect to the reference frame. At the inner core boundary a continuity condition for the magnetic field and the horizontal component of the electrical field apply.

#### See also:

The magnetic boundary conditions can be adjusted with the parameters *ktopb* and *kbotb* in the *&phys\_param* section of the input namelist.

### 3.4.3 Thermal boundary conditions and distribution of buoyancy sources

In many dynamo models, convection is simply driven by an imposed fixed super-adiabatic entropy contrast between the inner and outer boundaries. This approximation is however not necessarily the best choice, since for instance, in the present Earth, convection is thought to be driven by a combination of thermal and compositional buoyancy. Sources of heat are the release of latent heat of inner core solidification and the secular cooling of the outer and inner core, which can effectively be treated like a heat source. The heat loss from the core is controlled by the convecting mantle, which effectively imposes a condition of fixed heat flux at the core-mantle boundary on the dynamo. The heat flux is in that case spatially and temporally variable.

#### See also:

The thermal boundary conditions can be adjusted with the parameters *ktops* and *kbots* in the *&phys\_param* section of the input namelist.

## NUMERICAL TECHNIQUE

MagIC is a pseudo-spectral MHD code. This numerical technique was originally developed by P. Gilman and G. Glatzmaier for the spherical geometry. In this approach the unknowns are expanded into complete sets of functions in radial and angular directions: Chebyshev polynomials in the radial directions and spherical harmonic functions in the azimuthal and latitudinal directions. This allows to express all partial derivatives analytically. Employing orthogonality relations of spherical harmonic functions and using collocation in radius then lead to algebraic equations that are integrated in time with a mixed implicit/explicit time stepping scheme. The nonlinear terms and the Coriolis force are evaluated in the physical (or grid) space rather than in spectral space. Although this approach requires costly numerical transformations between the two representations (from spatial to spectral using Legendre and Fourier transforms), the resulting decoupling of all spherical harmonic modes leads to a net gain in computational speed. Before explaining these methods in more detail, we introduce the poloidal/toroidal decomposition.

## 4.1 Poloidal/toroidal decomposition

Any vector v that fulfills  $\nabla \cdot v = 0$  can be decomposed in a poloidal and toroidal part W and Z, respectively

$$v = \nabla \times (\nabla \times W e_r) + \nabla \times Z e_r.$$

Three unknown vector components are thus replaced by two scalar fields, the poloidal potential W and the toroidal potential Z. This decomposition is unique, aside from an arbitrary radial function f(r) that can be added to W or Z without affecting v.

In the anelastic approximation, such a decomposition can be used for the mass flux  $\tilde{\rho}u$  and the magnetic field B. This yields

$$\tilde{\rho} \boldsymbol{u} = \nabla \times (\nabla \times W \, \boldsymbol{e_r}) + \nabla \times Z \, \boldsymbol{e_r}$$

$$\boldsymbol{B} = \nabla \times (\nabla \times g \, \boldsymbol{e_r}) + \nabla \times h \, \boldsymbol{e_r}.$$
(4.1)

The two scalar potentials of a divergence free vector field can be extracted from its radial component and the radial component of its curl:

$$e_r \cdot v = -\Delta_H W,$$

$$e_r \cdot (\nabla \times B) = -\Delta_H Z,$$
(4.2)

where the operator  $\Delta_H$  denotes the horizontal part of the Laplacian:

$$\Delta_H = \frac{1}{r^2 \sin \theta} \frac{\partial}{\partial \theta} \left( \sin \theta \frac{\partial}{\partial \theta} \right) + \frac{1}{r^2 \sin^2 \theta} \frac{\partial^2}{\partial^2 \phi}.$$
 (4.3)

## 4.2 Spherical harmonic representation

Spherical harmonic functions  $Y_{\ell}^{m}$  are a natural choice for the horizontal expansion in colatitude  $\theta$  and longitude  $\phi$ :

$$Y_{\ell}^{m}(\theta,\phi) = P_{\ell}^{m}(\cos\theta) e^{im\phi},$$

where  $\ell$  and m denote spherical harmonic degree and order, respectively,  $P_{\ell}^{m}$  is an associated Legendre function. Different normalization are in use. Here we adopt a complete normalization so that the orthogonality relation reads

$$\int_0^{2\pi} d\phi \int_0^{\pi} \sin\theta \, d\theta \, Y_\ell^m(\theta,\phi) \, Y_{\ell'}^{m'}(\theta,\phi) = \delta_{\ell\ell'} \delta^{mm'}. \tag{4.4}$$

This means that

$$Y_{\ell}^{m}(\theta,\phi) = \sqrt{\frac{1}{2\pi}} \frac{(2\ell+1)(\ell-|m|)!}{2(\ell+|m|)!} P_{\ell}^{m}(\cos\theta) e^{im\phi} (-1)^{m},$$

For example, the spherical harmonic representation of the magnetic poloidal potential  $g(r, \theta, \phi)$ , truncated at degree and order  $\ell_{max}$ , then reads

$$g(r, \theta, \phi) = \sum_{\ell=0}^{\ell_{max}} \sum_{m=-\ell}^{\ell} g_{\ell m}(r) Y_{\ell}^{m}(\theta, \phi), \tag{4.5}$$

with

$$g_{\ell m}(r) = \frac{1}{\pi} \int_0^{\pi} d\theta \sin\theta \ g_m(r,\theta) \ P_{\ell}^m(\cos\theta), \tag{4.6}$$

$$g_m(r,\theta) = \frac{1}{2\pi} \int_0^{2\pi} d\phi \ g(r,\theta,\phi) \ e^{-im\phi}.$$
 (4.7)

The potential  $g(r, \theta, \phi)$  is a real function so that  $g_{\ell m}^{\star}(r) = g_{\ell, -m}(r)$ , where the asterisk denotes the complex conjugate. Thus, only coefficients with  $m \geq 0$  have to be considered. The same kind of expansion is made for the toroidal magnetic potential, the mass flux potentials, pressure and entropy (or temperature).

The equations (4.6) and (4.7) define a two-step transform from the longitude/latitude representation to the spherical harmonic representation  $(r, \theta, \phi) \longrightarrow (r, \ell, m)$ . The equation (4.5) formulates the inverse procedure  $(r, \ell, m) \longrightarrow (r, \theta, \phi)$ . Fast-Fourier transforms are employed in the longitudinal direction, requiring (at least)  $N_{\phi} = 2\ell_{max} + 1$  evenly spaced grid points  $\phi_i$ . MagIC relies on the Gauss-Legendre quadrature for evaluating the integral (4.6)

$$g_{\ell m}(r) = \frac{1}{N_{\theta}} \sum_{j=1}^{N_{\theta}} w_j g_m(r, \theta_j) P_{\ell}^m(\cos \theta_j),$$

where  $\theta_j$  are the  $N_{\theta}$  Gaussian quadrature points defining the latitudinal grid, and  $w_j$  are the respective weights. Prestored values of the associated Legendre functions at grid points  $\theta_j$  in combination with a FFT in  $\phi$  provide the inverse transform (4.5). Generally,  $N_{\phi}=2N_{\theta}$  is chosen, which provides isotropic resolution in the equatorial region. Choosing  $\ell_{max}=[\min(2N_{\theta},N_{\phi})-1]/3$  prevents aliasing errors.

## 4.2.1 Special relations

The action of a horizontal Laplacian (4.3) on spherical harmonics can be analytically expressed by

$$\Delta_H Y_{\ell}^m = -\frac{\ell(\ell+1)}{r^2} Y_{\ell}^m \,. \tag{4.8}$$

They are several useful recurrence relations for the Legendre polynomials that will be further employed to compute Coriolis forces and the  $\theta$  and  $\phi$  derivatives of advection and Lorentz forces:

$$\cos\theta \,\partial P_{\ell}^{m} = c_{\ell+1}^{m} \, P_{\ell+1}^{m} + c_{\ell}^{m} \, P_{\ell-1}^{m} \,, \tag{4.9}$$

and

$$\sin \theta \, \frac{\partial P_{\ell}^{m}}{\partial \theta} = (\ell - 1) \, c_{\ell+1}^{m} \, P_{\ell+1}^{m} - (\ell + 2) \, c_{\ell}^{m} \, P_{\ell-1}^{m} \,, \tag{4.10}$$

where  $c_{\ell}^{m}$  is defined by

$$c_{\ell}^{m} = \sqrt{\frac{(\ell+m)(\ell-m)}{(2\ell-1)(2\ell+1)}}.$$
(4.11)

## 4.3 Radial representation

In MagIC, the radial dependencies are expanded into complete sets of functions: the Chebyshev polynomials C(x). The polynomial of degree n is defined by

$$C_n(x) = \cos [n \operatorname{arccos}(x)] - 1 \le x \le 1.$$

When truncating at degree N, the radial expansion of the poloidal magnetic potential reads

$$g_{\ell m}(r) = \sum_{n=0}^{N} g_{\ell m n} \, \mathcal{C}_n(r),$$
 (4.12)

with

$$g_{\ell mn} = \frac{2 - \delta_{n0}}{\pi} \int_{-1}^{1} \frac{dx \, g_{\ell m}(r(x)) \, \mathcal{C}_n(x)}{\sqrt{1 - r^2}}.$$
 (4.13)

The Chebyshev definition space  $(-1 \le x \le 1)$  is then linearly mapped onto a radius range  $(r_i \le r \le r_o)$  by

$$x(r) = 2\frac{r - r_i}{r_2 - r_i} - 1. (4.14)$$

In addition, nonlinear mapping can be defined to modify the radial dependence of the grid-point density.

When choosing the  $N_r$  extrema of  $C_{N_r-1}$  as radial grid points,

$$x_k = \cos\left(\pi \frac{(k-1)}{N_r - 1}\right) , \quad k = 1, 2, \dots, N_r,$$
 (4.15)

the values of the Chebyshev polynomials at these points are simply given by the cosine functions:

$$C_{nk} = C_n(x_k) = \cos\left(\pi \frac{n(k-1)}{N_r - 1}\right).$$

This particular choice has two advantages. For one, the grid points become denser toward the inner and outer radius and better resolve potential thermal and viscous boundary layers. In addition, FFTs can be employed to switch between grid representation (4.12) and Chebyshev representations (4.13), rendering this procedure a fast-Chebyshev transform. Choosing  $N_r > N$  provides radial dealiasing.

### See also:

The Chebyshev (Gauss-Lobatto) grid is defined in the module <code>chebyshev\_polynoms\_mod</code>. The cosine transforms are computed in the modules <code>cosine\_transform</code> and <code>fft\_fac\_mod</code>.

## 4.4 Spectral equations

We have now introduced the necessary tools for deriving the spectral equations. Taking the **radial components** of the Navier-Stokes equation and the induction equation provides the equations for the poloidal potentials  $W(r, \theta, \phi)$  and  $g(r, \theta, \phi)$ . The **radial component of the curl** of these equations provides the equations for the toroidal counterparts  $Z(r, \theta, \phi)$  and  $h(r, \theta, \phi)$ . The pressure remains an additional unknown. Hence one more equation involving  $W_{\ell mn}$  and  $p_{\ell mn}$  is required. It is obtained by taking the **horizontal divergence** of the Navier-Stokes equation.

Expanding all potentials in spherical harmonics and Chebyshev polynomials, multiplying with  $Y_{\ell}^{m*}$ , and integrating over spherical surfaces (while making use of the orthogonality relation (4.4) results in equations for the coefficients  $W_{\ell mn}$ ,  $Z_{\ell mn}$ ,  $g_{\ell mn}$ ,  $h_{\ell mn}$ ,  $P_{\ell mn}$  and  $s_{\ell mn}$ , respectively.

## **4.4.1** Equation for the poloidal potential W

The temporal evolution of W is obtained by taking  $e_r$  of each term entering the Navier-Stokes equation. For the time-derivative, one gets using (4.2):

$$\tilde{\rho} \boldsymbol{e_r} \cdot \left(\frac{\partial \boldsymbol{u}}{\partial t}\right) = \frac{\partial}{\partial t} (\boldsymbol{e_r} \cdot \tilde{\rho} \boldsymbol{u}) = -\Delta_H \frac{\partial W}{\partial t}.$$

For the viscosity term, one gets

$$\begin{split} \boldsymbol{e_r} \cdot \boldsymbol{\nabla} \cdot \mathbf{S} &= - \, \nu \, \Delta_H \left[ \frac{\partial^2 W}{\partial r^2} + \left\{ 2 \frac{d \ln \nu}{dr} - \frac{1}{3} \frac{d \ln \tilde{\rho}}{dr} \right\} \frac{\partial W}{\partial r} \right. \\ &- \left. \left\{ -\Delta_H + \frac{4}{3} \left( \frac{d^2 \ln \tilde{\rho}}{dr^2} + \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{1}{r} \left[ 3 \frac{d \ln \nu}{dr} + \frac{d \ln \tilde{\rho}}{dr} \right] \right) \right\} W \right], \end{split}$$

**Note:** In case of a constant kinematic viscosity, the  $d \ln \nu / dr$  terms vanish. If in addition, the background density is constant, the  $d \ln \tilde{\rho} / dr$  terms also vanish. In that Boussinesq limit, this viscosity term would then be simplified as

$$e_{r} \cdot \Delta u = -\Delta_{H} \left[ \frac{\partial^{2} W}{\partial r^{2}} + \Delta_{H} W \right]$$

Using Eq. (4.8) then allows to finally write the time-evolution equation for the poloidal potential  $W_{\ell mn}$ :

$$E \frac{\ell(\ell+1)}{r^{2}} \left[ \left\{ \frac{\partial}{\partial t} + \nu \frac{\ell(\ell+1)}{r^{2}} + \frac{4}{3} \nu \left( \frac{d^{2} \ln \tilde{\rho}}{dr^{2}} + \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{1}{r} \left[ 3 \frac{d \ln \nu}{dr} + \frac{d \ln \tilde{\rho}}{dr} \right] \right) \right\} C_{n}$$

$$-\nu \left\{ 2 \frac{d \ln \nu}{dr} - \frac{1}{3} \frac{d \ln \tilde{\rho}}{dr} \right\} C'_{n}$$

$$-\nu C''_{n} \qquad \right] \quad W_{\ell m n}$$

$$+ \left[ C'_{n} - \frac{d \ln \tilde{\rho}}{dr} C_{n} \right] \qquad P_{\ell m n}$$

$$- \left[ \frac{Ra E}{Pr} \tilde{\rho} g(r) \right] C_{n} \qquad s_{\ell m n}$$

$$= \mathcal{N}^{W} = \int d\Omega Y_{\ell}^{m \star} \mathbf{e}_{r} \cdot \mathbf{F}$$

$$(4.16)$$

Here,  $d\Omega$  is the spherical surface element. We use the summation convention for the Chebyshev index n. The radial derivatives of Chebyshev polynomials are denoted by primes.

#### See also:

The exact computation of the linear terms of (4.16) are coded in the subroutines <code>get\_wpMat</code>

## 4.4.2 Equation for the toroidal potential Z

The temporal evolution of Z is obtained by taking the radial component of the curl of the Navier-Stokes equation (i.e.  $e_r \cdot \nabla \times$ ). For the time derivative, one gets using (4.2):

$$e_r \cdot \nabla \times \left( \frac{\partial \tilde{\rho} u}{\partial t} \right) = \frac{\partial}{\partial t} (e_r \cdot \nabla \times \tilde{\rho} u) = -\frac{\partial}{\partial t} (\Delta_H Z) = -\Delta_H \frac{\partial Z}{\partial t}$$

The pressure gradient, one has

$$\nabla \times \left[ \tilde{\rho} \nabla \left( \frac{p'}{\tilde{\rho}} \right) \right] = \nabla \tilde{\rho} \times \nabla \left( \frac{p'}{\tilde{\rho}} \right) + \underbrace{\tilde{\rho} \nabla \times \left[ \nabla \left( \frac{p'}{\tilde{\rho}} \right) \right]}_{=0}.$$

This expression has no component along  $e_r$ , as a consequence, there is no pressure gradient contribution here. The gravity term also vanishes as  $\nabla \times (\tilde{\rho}g(r)e_r)$  has no radial component.

$$\begin{split} \boldsymbol{e_r} \cdot \boldsymbol{\nabla} \times \left[ \boldsymbol{\nabla} \cdot \boldsymbol{\mathsf{S}} \right] &= -\nu \, \Delta_H \left[ \frac{\partial^2 Z}{\partial r^2} + \left( \frac{d \ln \nu}{dr} - \frac{d \ln \tilde{\rho}}{dr} \right) \, \frac{\partial Z}{\partial r} \right. \\ &\left. - \left( \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \frac{d \ln \nu}{dr} + \frac{d^2 \ln \tilde{\rho}}{dr^2} + \frac{2}{r} \frac{d \ln \tilde{\rho}}{dr} - \Delta_H \right) Z \right]. \end{split}$$

**Note:** Once again, this viscous term can be greatly simplified in the Boussinesq limit:

$$oldsymbol{e_r} \cdot oldsymbol{
abla} imes (\Delta oldsymbol{u}) = -\Delta_H \left[ rac{\partial^2 Z}{\partial r^2} + \Delta_H \, Z 
ight]$$

Using Eq. (4.8) then allows to finally write the time-evolution equation for the poloidal potential  $Z_{\ell mn}$ :

$$E \frac{\ell(\ell+1)}{r^{2}} \left[ \left\{ \frac{\partial}{\partial t} + \nu \frac{\ell(\ell+1)}{r^{2}} + \nu \left( \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \frac{d \ln \nu}{dr} + \frac{d^{2} \ln \tilde{\rho}}{dr^{2}} + \frac{2}{r} \frac{d \ln \tilde{\rho}}{dr} \right) \right\} C_{n}$$

$$-\nu \left( \frac{d \ln \nu}{dr} - \frac{d \ln \tilde{\rho}}{dr} \right) C'_{n}$$

$$-\nu C''_{n} \qquad \right] \quad Z_{\ell m n}$$

$$= \mathcal{N}^{Z} = \int d\Omega Y_{\ell}^{m \star} \mathbf{e}_{r} \cdot (\nabla \times \mathbf{F})$$

$$(4.17)$$

#### See also:

The exact computation of the linear terms of (4.17) are coded in the subroutines get\_zMat

### **4.4.3** Equation for pressure *P*

The evolution of equation for pressure is obtained by taking the horizontal divergence (i.e.  $\nabla_H \cdot$ ) of the Navier-Stokes equation. This operator is defined such that

$$\nabla_H \cdot \boldsymbol{a} = r \sin \frac{\partial (\sin \theta \, a_\theta)}{\partial \theta} + r \sin \frac{\partial a_\phi}{\partial \phi}$$

This relates to the total divergence via:

$$oldsymbol{
abla} \cdot oldsymbol{a} = rac{1}{r^2} rac{\partial (r^2 a_r)}{\partial r} + oldsymbol{
abla}_H \cdot oldsymbol{a}.$$

The time-derivative term is thus expressed by

$$\begin{split} \boldsymbol{\nabla}_{H} \cdot \left( \tilde{\rho} \frac{\partial \boldsymbol{u}}{\partial t} \right) &= \frac{\partial}{\partial t} \left[ \boldsymbol{\nabla}_{H} \cdot (\tilde{\rho} \boldsymbol{u}) \right] \\ &= \frac{\partial}{\partial t} \left[ \boldsymbol{\nabla} \cdot (\tilde{\rho} \boldsymbol{u}) - \frac{1}{r^{2}} \frac{\partial (r^{2} \tilde{\rho} u_{r})}{\partial r} \right] \\ &= -\frac{\partial}{\partial t} \left[ \frac{\partial (\tilde{\rho} u_{r})}{\partial r} + \frac{2\tilde{\rho} u_{r}}{r} \right] \\ &= \frac{\partial}{\partial t} \left[ \frac{\partial (\Delta_{H} W)}{\partial r} + \frac{2}{r} \Delta_{H} W \right] \\ &= \Delta_{H} \frac{\partial}{\partial t} \left( \frac{\partial W}{\partial r} \right) \end{split}$$

We note that the gravity term vanishes since  $\nabla_H \cdot (\tilde{\rho}g(r)e_r) = 0$ . Concerning the pressure gradient, one has

$$-\boldsymbol{\nabla}_{H}\cdot\left[\tilde{\rho}\boldsymbol{\nabla}\left(\frac{p'}{\tilde{\rho}}\right)\right]=-\left\{\boldsymbol{\nabla}\cdot\left[\tilde{\rho}\boldsymbol{\nabla}\left(\frac{p'}{\tilde{\rho}}\right)\right]-\frac{1}{r^{2}}\frac{\partial}{\partial r}\left[r^{2}\tilde{\rho}\frac{\partial}{\partial r}\left(\frac{p'}{\tilde{\rho}}\right)\right]\right\}=-\Delta_{H}\,p'.$$

The viscosity term then reads

$$\begin{split} \boldsymbol{\nabla}_{H} \cdot (\boldsymbol{\nabla} \cdot \boldsymbol{\mathsf{S}}) = & \nu \, \Delta_{H} \left[ \frac{\partial^{3} W}{\partial r^{3}} + \left( \frac{d \ln \nu}{dr} - \frac{d \ln \tilde{\rho}}{dr} \right) \frac{\partial^{2} W}{\partial r^{2}} \right. \\ & - \left[ \frac{d^{2} \ln \tilde{\rho}}{dr^{2}} + \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \left( \frac{d \ln \nu}{dr} + \frac{d \ln \tilde{\rho}}{dr} \right) - \Delta_{H} \right] \frac{\partial W}{\partial r} \\ & - \left( \frac{2}{3} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} + \frac{d \ln \nu}{dr} \right) \Delta_{H} W \right]. \end{split}$$

**Note:** Once again, this viscous term can be greatly simplified in the Boussinesq limit:

$$\nabla_{H} \cdot (\Delta \boldsymbol{u}) = -\Delta_{H} \left[ \frac{\partial^{3} W}{\partial r^{3}} + \Delta_{H} \frac{\partial W}{\partial r} - \frac{2}{r} \Delta_{H} W \right]$$

Using Eq. (4.8) then allows to finally write the equation for the pressure  $P_{\ell mn}$ :

$$E\frac{\ell(\ell+1)}{r^2} \left[ -\nu \left( \frac{2}{3} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} + \frac{d \ln \nu}{dr} \right) \frac{\ell(\ell+1)}{r^2} C_n \right]$$

$$\left\{ \frac{\partial}{\partial t} + \nu \frac{\ell(\ell+1)}{r^2} + \nu \left[ \frac{d^2 \ln \tilde{\rho}}{dr^2} + \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \left( \frac{d \ln \nu}{dr} + \frac{d \ln \tilde{\rho}}{dr} \right) \right] \right\} C'_n$$

$$-\nu \left( \frac{d \ln \nu}{dr} - \frac{d \ln \tilde{\rho}}{dr} \right) C''_n$$

$$-\nu C'''_n \qquad \left[ W_{\ell m n} \right]$$

$$+ \left[ \frac{\ell(\ell+1)}{r^2} \right] C_n \qquad P_{\ell m n}$$

$$= \mathcal{N}^P = -\int d\Omega Y_\ell^{m*} \nabla_H \cdot \mathbf{F}$$

$$(4.18)$$

#### See also:

The exact computation of the linear terms of (4.18) are coded in the subroutines get\_wpMat

**Note:** We note that the terms on the left hand side of (4.16), (4.17) and (4.18) resulting from the viscous term, the pressure gradient, the buoyancy term, and the explicit time derivative completely decouple in spherical harmonic degree and order.

The terms that do not decouple, namely Coriolis force, Lorentz force and advection of momentum, are collected on the right-hand side of (4.16), (4.17) and (4.18) into the forcing term F:

$$\boldsymbol{F} = -2\,\tilde{\rho}\,\boldsymbol{e_z} \times \boldsymbol{u} - E\,\tilde{\rho}\,\boldsymbol{u} \cdot \boldsymbol{\nabla}\,\boldsymbol{u} + \frac{1}{Pm}\left(\boldsymbol{\nabla} \times \boldsymbol{B}\right) \times \boldsymbol{B} \tag{4.19}$$

Resolving F into potential functions is not required. Its numerical evaluation is discussed below.

## **4.4.4 Equation for entropy** s

The equation for the entropy (or temperature in the Boussinesq limit) is given by

$$\frac{1}{Pr} \left[ \left( Pr \frac{\partial}{\partial t} + \kappa \frac{\ell(\ell+1)}{r^2} \right) C_n \right]$$

$$-\kappa \left( \frac{d \ln \kappa}{dr} + \frac{d \ln \tilde{\rho}}{dr} + + \frac{d \ln \tilde{T}}{dr} + \frac{2}{r} \right) C'_n$$

$$-\kappa C''_n \qquad \left] \quad s_{\ell mn} \right]$$

$$= \mathcal{N}^S = -\int d\Omega Y_{\ell}^{m\star} \left[ \mathbf{u} \cdot \nabla s + \frac{Pr Di}{Ra} \frac{1}{\tilde{\rho} \tilde{T}} \left( \Phi_{\nu} + \frac{\lambda}{Pm^2 E} j^2 \right) \right]$$
(4.20)

In this expression,  $j = \nabla \times B$  is the current. Once again, the numerical evaluation of the right-hand-side (i.e. the non-linear terms) is discussed *below*.

#### See also:

The exact computation of the linear terms of (4.20) are coded in the subroutines get sMat

## 4.4.5 Equation for the poloidal magnetic potential g

The equation for the poloidal magnetic field coefficient reads

$$\begin{bmatrix}
\frac{\ell(\ell+1)}{r^2} \left[ \left( \frac{\partial}{\partial t} + \frac{1}{Pm} \lambda \frac{\ell(\ell+1)}{r^2} \right) C_n \\
-\frac{1}{Pm} \lambda C_n'' \right] g_{\ell m n}
\end{bmatrix}$$

$$= \mathcal{N}^g = \int d\Omega Y_\ell^{m \star} \mathbf{e}_r \cdot \mathbf{D}$$
(4.21)

#### See also:

The exact computation of the linear terms of (4.21) are coded in the subroutines  $get\_bMat$ 

## 4.4.6 Equation for the toroidal magnetic potential h

The equation for the toroidal magnetic field coefficient reads

$$\frac{\ell(\ell+1)}{r^2} \left[ \left( \frac{\partial}{\partial t} + \frac{1}{Pm} \lambda \frac{\ell(\ell+1)}{r^2} \right) C_n - \frac{1}{Pm} \frac{d\lambda}{dr} C'_n - \frac{1}{Pm} \lambda C''_n - \frac{1}{Pm} \lambda C''_n \right] h_{\ell m n}$$

$$= \mathcal{N}^h = \int d\Omega Y_\ell^{m \star} \mathbf{e}_{\mathbf{r}} \cdot (\mathbf{\nabla} \times \mathbf{D})$$
(4.22)

#### See also:

The exact computation of the linear terms of (4.22) are coded in the subroutines get\_bMat

We have now derived a full set of equations (4.16), (4.17), (4.18), (4.20), (4.21) and (4.22), each describing the evolution of a single spherical harmonic mode of the six unknown fields (assuming that the terms on the right hand side are given). Each equation couples N+1 Chebyshev coefficients for a given spherical harmonic mode  $(\ell, m)$ . Typically, a collocation method is employed to solve for the Chebyshev coefficients. This means that the equations are required to be exactly satisfied at N-1 grid points defined by the equations (4.14) and (4.15). Excluded are the points  $r=r_i$  and  $r=r_o$ , where the *boundary conditions* provide additional constraints on the set of Chebyshev coefficients.

## 4.5 Time-stepping schemes

Implicit time stepping schemes theoretically offer increased stability and allow for larger time steps. However, fully implicit approaches have the disadvantage that the nonlinear-terms couple all spherical harmonic modes. The potential gain in computational speed is therefore lost at higher resolution, where one very large matrix has to be dealt with rather than a set of much smaller ones. Similar considerations hold for the Coriolis force, one of the dominating forces in the system and therefore a prime candidate for implicit treatment. However, the Coriolis term couples modes  $(\ell, m, n)$  with  $(\ell+1, m, n)$  and  $(\ell-1, m, n)$  and also couples poloidal and toroidal flow potentials. An implicit treatment of the Coriolis term therefore also results in a much larger (albeit sparse) inversion matrix.

W consequently adopt in **MagIC** a mixed implicit/explicit algorithm. Nonlinear and Coriolis terms, collected on the right hand side of equations (4.16), (4.17), (4.18), (4.20), (4.21) and (4.22) are treated explicitly with a second order Adams-Bashforth . Terms collected on the left hand side are time-stepped with an implicit modified Crank-Nicolson algorithm. While the equations are coupled radially, they decouple for all spherical harmonic modes.

**Note:** The poloidal flow potential (4.16) and the pressure (4.18) are nevertheless coupled for a given spherical harmonic mode.

As an example, we derive the time stepping equation for the poloidal magnetic potential of degree  $\ell$  and order m, denoting the explicit nonlinear term at radial grid point  $r_k$  with

$$D_{k\ell m}(t) = \int d\Omega Y_{\ell}^{m\star} e_{r} \cdot \boldsymbol{D}(t, r_{k}, \theta, \phi) .$$

After discretization of the partial time derivative,  $\partial g_{\ell mn}/\partial t = [g_{\ell mn}(t+\delta t) - g_{\ell mn}(t)]/\delta t$  where  $\delta t$  is the time step, we can formulate the left hand side of (4.21) as a matrix multiplication. The matrices A and G are defined by

$$A_{kn} = \frac{\ell(\ell+1)}{r_k^2} \, \frac{1}{\delta t} \mathcal{C}_{nk}$$

and

$$G_{kn} = \frac{\ell(\ell+1)}{r_k^2} \frac{1}{Pm} \left( \frac{\ell(\ell+1)}{r_k^2} \mathcal{C}_{nk} - \mathcal{C}_{nk}'' \right) ,$$

where  $C_{nk} = C_n(r_k)$ . The matrices depend on  $\ell$  but not on m. Advancing time from t to  $t + \delta t$  is then a matter of solving

$$(A_{kn} + \alpha G_{kn}) \ g_{\ell mn}(t + \delta t) = (A_{kn} - (1 - \alpha)G_{kn}) \ g_{\ell mn}(t) + \frac{3}{2}D_{k\ell m}(t) - \frac{1}{2}D_{k\ell m}(t - \delta t) \ .$$

The classical Crank-Nicholson scheme is recovered for  $\alpha=0.5$ , but it seems that a slightly larger weight of  $\alpha=0.6$  helps to stabilize the time integration. Since the stability requirements limiting  $\delta t$  will usually change during a computational run, the time step should be adjusted accordingly. The matrix G remains unchanged, but A has to be updated whenever  $\delta t$  is changed. This, in turn, requires a new triangulation of matrix  $A_{kn}+\alpha G_{kn}$ , which is then stored for subsequent time steps until the next adjustment of  $\delta t$  is in order.

Courant's condition offers a guideline concerning the value of  $\delta t$ , demanding that  $\delta t$  should be smaller than the advection time between two grid points. Strong Lorentz forces require an additional stability criterion that is obtained by replacing the flow speed by Alfvén's velocity in a modified Courant criterion. The explicit treatment of the Coriolis force requires that the time step is limited to a fraction of the rotation period, which may be the relevant criterion at low Ekman number when flow and magnetic field remain weak. Non-homogeneous grids and other numerical effects generally require an additional safety factor in the choice of  $\delta t$ .

### 4.6 Coriolis force and non-linear terms

$$\mathcal{A}_r = -\tilde{\rho} \left( u_r \frac{\partial u_r}{\partial r} + \frac{u_\theta}{r} \frac{\partial u_r}{\partial \theta} + \frac{u_\phi}{r \sin \theta} \frac{\partial u_r}{\partial \phi} - \frac{u_\theta^2 + u_\phi^2}{r} \right) + \frac{1}{Pm} \left( j_\theta B_\phi - j_\phi B_\theta \right) , \tag{4.23}$$

$$\mathcal{A}_{\theta} = -\tilde{\rho} \left( u_r \frac{\partial u_{\theta}}{\partial r} + \frac{u_{\theta}}{r} \frac{\partial u_{\theta}}{\partial \theta} + \frac{u_{\phi}}{r \sin \theta} \frac{\partial u_{\theta}}{\partial \phi} + \frac{u_r u_{\theta}}{r} - \frac{\cos \theta}{r \sin \theta} u_{\phi}^2 \right) + \frac{1}{Pm} \left( j_{\phi} B_r - j_r B_{\phi} \right) , \tag{4.24}$$

$$\mathcal{A}_{\phi} = -\tilde{\rho} \left( u_r \frac{\partial u_{\phi}}{\partial r} + \frac{u_{\theta}}{r} \frac{\partial u_{\phi}}{\partial \theta} + \frac{u_{\phi}}{r \sin \theta} \frac{\partial u_{\phi}}{\partial \phi} + \frac{u_r u_{\phi}}{r} + \frac{\cos \theta}{r \sin \theta} u_{\theta} u_{\phi} \right) + \frac{1}{Pm} \left( j_r B_{\theta} - j_{\theta} B_r \right) , \tag{4.25}$$

## 4.7 Boundary conditions and inner core

### 4.7.1 Mechanical boundary conditions

Since the system of equations is formulated on a radial grid, boundary conditions can simply be satisfied by replacing the collocation equation at grid points  $r_i$  and  $r_o$  with appropriate expressions. The condition of zero radial flow on the boundaries implies

$$C_n(r)W_{\ell mn} = 0 \text{ at } r = r_i, r_o . \tag{4.26}$$

Note that the summation convention with respect to radial modes n is used again. The no-slip condition further requires that the horizontal flow components also have to vanish, provided the two boundaries are at rest. This condition is fulfilled when

$$C'_n(r)W_{\ell mn} = 0 \quad \text{at} \quad r = r_i, r_o \tag{4.27}$$

and

$$C_n(r)Z_{\ell mn} = 0 \text{ at } r = r_i, r_o \tag{4.28}$$

for all spherical harmonic modes  $(\ell, m)$ . The conditions (4.26)-(4.28) replace the poloidal flow potential equations (4.16) and the pressure equation (4.18), respectively, at the collocation points  $r_i$  and  $r_o$ .

If the inner-core and/or the mantle are allowed to react to torques, a condition based on the conservation of angular momentum replaces condition (4.28) for the mode ( $\ell = 1, m = 0$ ):

$$\mathsf{I} \frac{\partial \boldsymbol{\omega}}{\partial t} = \mathbf{\Gamma} \ .$$

The tensor I denotes the moment of inertia of inner core or mantle, respectively,  $\omega$  is the mantle or inner-core rotation rate relative to that of the reference frame, and  $\Gamma$  is the respective torque.

**Free-slip boundary conditions** require that the viscous stress vanishes, which in turn implies that the non-diagonal components  $Sr_{r\phi}$  and  $S_{r\theta}$  of the rate-of-strain tensor vanish. Translated to the spectral representation this requires

$$\left[\mathcal{C}_n''(r) - \left(\frac{2}{r} + \frac{d\ln\tilde{\rho}}{dr}\right)\mathcal{C}_n'(r)\right]W_{\ell mn} = 0 \text{ and } \left[\mathcal{C}_n'(r) - \left(\frac{2}{r} + \frac{d\ln\tilde{\rho}}{dr}\right)\mathcal{C}_n(r)\right]z_{\ell mn} = 0.$$

## 4.7.2 Magnetic boundary conditions and inner core

Magnetic boundary conditions at the interface with an insulating mantle or insulating inner core are similarly implemented. The toroidal magnetic field cannot enter any insulator and therefore has to vanish at the boundary

$$C_n(r)h_{\ell mn}=0$$
 at  $r=r_i$  and/or  $r=r_o$ .

Matching conditions for the poloidal magnetic field with a source-free external potential field require that the following equations are satisfied at the boundary grid points:

$$C'_n(r)g_{\ell mn} - C_n(r)\frac{\ell+1}{r}g_{\ell mn} = 0$$
 at  $r = r_i$ ,

$$\mathcal{C}_n'(r)g_{\ell mn} + \mathcal{C}_n(r)\frac{\ell}{r}g_{\ell mn} = 0$$
 at  $r = r_o$ .

If the inner core is modeled as an electrical conductor, a simplified dynamo equation has to be solved in which the fluid flow is replaced by the solid-body rotation of the inner core. The latter is described by a single toroidal flow mode  $(\ell=1,m=0)$ . The resulting nonlinear terms can be expressed by a simple spherical harmonic expansion, where the superscript I denotes values in the inner core and  $\omega_I$  its differential rotation rate:

$$\int d\Omega Y_{\ell}^{m\star} e_{r} \cdot \left[ \nabla \times \left( u^{I} \times B^{I} \right) \right] = -i \omega_{I} m \frac{\ell(\ell+1)}{r^{2}} g_{\ell m}^{I}(r) , \qquad (4.29)$$

$$\int d\Omega Y_{\ell}^{m\star} \mathbf{e}_{r} \cdot \left[ \nabla \times \nabla \times \left( \mathbf{u}^{I} \times \mathbf{B}^{I} \right) \right] = -i \omega_{I} m \frac{\ell(\ell+1)}{r^{2}} h_{\ell m}^{I}(r)$$
(4.30)

The expensive back and forth transformations between spherical harmonic and grid representations are therefore not required for advancing the inner-core magnetic field in time.

In the inner core the magnetic potentials are again conveniently expanded into Chebyshev polynomials. The Chebyshev variable x spans the whole diameter of the inner core, so that grid points are dense near the inner-core boundary but sparse in the center. The mapping is given by:

$$x(r) = \frac{r}{r_i} , -r_i \le r \le r_i .$$
 (4.31)

Each point in the inner core is thus represented twice, by grid points  $(r, \theta, \phi)$  and  $(-r, \pi - \theta, \phi + \pi)$ . Since both representations must be identical, this imposes a symmetry constraint that can be fulfilled when the radial expansion comprises only polynomials of even order:

$$g_{\ell m}^{I}(r) = \left(\frac{r}{r_i}\right)^{\ell+1} \sum_{i=0}^{M-1} g_{\ell m \, 2i}^{I} \, \mathcal{C}_{2i}(r) \ . \tag{4.32}$$

An equivalent expression holds for the toroidal potential in the inner core. FFTs can again by employed efficiently for the radial transformation, using the M extrema of  $C_{2M-1}(r)$  with x > 0 as grid points.

The sets of spectral magnetic field equations for the inner and the outer core are coupled via continuity equations for the magnetic field and the horizontal electric field. Continuity of the magnetic field is assured by (i) continuity of the toroidal potential, (ii) continuity of the poloidal potential, and (iii) continuity of the radial derivative of the latter. Continuity of the horizontal electric field demands (iv) that the radial derivative of the toroidal potential is continuous, provided that the horizontal flow and the electrical conductivity are continuous at the interface. These four conditions replace the spectral equations (4.21), (4.22) on the outer-core side and equations (4.29), (4.30) on the inner-core side. Employing free-slip conditions or allowing for electrical conductivity differences between inner and outer core leads to more complicated and even non-linear matching conditions.

**CHAPTER** 

**FIVE** 

### CONTRIBUTING TO THE CODE

MagIC is an open-source code, we thus value any possible contribution! There are several ways to directly contribute to the code:

#### Contribute

- **Do you want to contribute to the code?** Just clone the code and start modyfing it. Make sure that your modifications *don't alter the code*, try to *document your changes* as much as you can and follow the recommended *Fortran coding style*.
- **Do you want to improve the documentation?** Feel free to document some missing features. The documentation is stored in the directory \$MAGIC\_HOME/doc/sphinx and relies on the documenting tool Sphinx. Some recommendations regarding documentation can be found *below*.
- Did you find a bug? Issues and feature requests should be raised in the github tracker.

## 5.1 Checking the consistency of the code

It is frequently required to check the consistency of the code, especially after the implementation of new features. For this reason, we have the Perl script magic\_checks.pl, located in the directory \$MAGIC\_HOME/samples/, which tests the compilation of the code and it's results against a set of standard solutions in sample directories to check if the code produces the correct output. It has been initially ported from the auto-test subroutines of the pencil-code developed by W. Dobler and adapted to the MagIC code.

You can run it as follows:

```
./magic_checks.pl <options>
```

### It supports the following options:

```
-h,
    --help
                         Show usage overview
-c,
    --clean
                         Clean the directories when it is finished
    --all
                         All auto-tests are computed
-a,
    --level=LEV
                         Run only tests from level LEV
    --max-level=LEV
                         Run all tests below with level <= LEV (default: 0)
    --no-recompile
                         Compile only once
    --hybrid
                         Run the hybrid version
```

The level=LEV defines the priority level of check and validation of the code. It has the following levels of checking:

Level	Cases to check (subdirectories)		
0	<ul> <li>Boussinesq dynamo benchmark (Christensen et al., 2001) - start from zero (dynamo_benchmark)</li> <li>Variable transport properties (viscosity, thermal diffusivity and electrical diffusivity) in an anelastic convective model (varProps)</li> <li>Boussinesq dynamo benchmark (Christensen et al., 2001) - start from a saturated state (boussBenchSat)</li> </ul>		
1	<ul> <li>Test reading and writing of restart files (testRestart)</li> <li>Test different grid truncations (testTruncations)</li> <li>Test mapping on to a new grid (testMapping)</li> <li>Test different outputs produced (testOutputs)</li> <li>Test different radial outputs - *R.TAG (testRadialOutputs)</li> </ul>		
2	Hydrodynamic anelastic benchmark (Jones et al., 2011) (hydro_bench_anel)		
3	$ \begin{array}{llllllllllllllllllllllllllllllllllll$		

## 5.2 Advices when contributing to the code

- Before committing your modifications always make sure that the auto-tests pass correctly.
- Try to follow the same coding style rules as in the rest of the code:
  - 1. Never use TABS but always SPACES instead
  - 2. Use 3 spaces for indentation

**Note:** These two rules can be easily set in your \$HOME/.vimrc file if you use vim:

```
au FileType fortran set shiftwidth=3
au FileType fortran set tabstop=3
au FileType fortran set expandtab
```

- 3. Never use capital letters for variable declaration
- 4. Never use dimension (len) for declaring array but rather real (cp) :: data(len)
- 5. Always use the default precisions when introducing new variables (cp)

These rules try to follow the general recommendations on modern fortran programming that can be found on www.fortran90.org or in the book Modern Fortran - style and usage by N. S. Clerman and W. Spector.

## 5.3 Building the documentation and contributing to it

The documentation is generated using Sphinx. To build it you'll thus need to install this python module on your machine. This is in general directly available on most of the Linux distributions under the name python-sphinx.

### Once installed, just go to the documentation directory

\$ cd \$MAGIC\_HOME/doc/sphinx

#### and build the html documentation

\$ make html

The complete documentation will then be built in a local directory named  $MAGIC_HOME/doc/sphinx/.build/html$ .

If LaTeX is installed on your work station, it is also possible to build the corresponding manual of the documentation in the pdf format:

\$ make latexpdf

The resulting pdf is then generated in a local directory named \$MAGIC\_HOME/doc/sphinx/.build/latex.

It is pretty straightforward to contribute to the documentation by simply adding some contents to the different rst files. Informations about reStructuredText syntax can be found on www.sphinx-doc.org, while helpful CheatSheet are accessible here or there.

**CHAPTER** 

SIX

### INPUT PARAMETERS

True runtime input parameters are read from STDIN as namelists, a Fortran feature. A namelist is identified by its unique name &name. The name-statement is followed by the parameters that are part of the namelist in the format parameter=value,. The namelist is closed by a backslash. The subroutine defaultNamelists (in the module Namelist.f90) defines a default value for each parameter. Only the parameters whose value should differ from its default have to be stated in the namelist.

An example for the short namelist defining inner core parameters is

```
&inner_core
  sigma_ratio = 1.0,
  nRotIc = 1
```

Comas can be used to seperate namelist entries since they are not interpreted by the code.

Magic uses the following eight namelists:

#### **Namelists**

- 1. & grid for resolution
- 2. &control for control parameters and numerical parameters.
- 3. &phys\_param for the physical parameters.
- 4. &B\_external for setting up an external field contribution
- 5. & start\_field to define the starting fields.
- 6. &output\_control for defining the output.
- 7. &mantle for setting mantle parameters.
- 8. &inner\_core for setting inner core parameters.

The number of possible input parameters has grown to more than 100/150. Don't be confused by all the possible options though, since all parameters are internally set to a useful default value!

Practically, in a production run, the number of parameters you may want to adjust is thus much smaller. As an example, the following namelist shows you how to initiate and quickly run one of the anelastic benchmarks by (Jones et al., 2011):

```
&grid
  n_r_max = 97, ! 97 radial grid points
  n_cheb_max = 95,
  n_phi_tot = 288, ! 288 points in the azimuthal direction
  n_r_ic_max = 17,
  n_cheb_ic_max=15,
  minc = 1,
//
&control
  mode = 1, ! This is a non-magnetic case
```

```
="test",
n_time_steps=50000, ! Number of time steps
courfac =2.5D0,
alffac =1.0D0,
dtmax =1.0D-4, ! Maximum allowed time-step
n\_cour\_step = 5,
alpha =0.6D0,
runHours =23, ! Run time (hours)
runMinutes =30, ! Run time (minutes)
&phys_param
ra =1.48638035D5, ! Rayleigh number
           =1.0D-3, ! Ekman number
pr
           =1.0D0, ! Prandtl number
strat =5.D0, ! Density contrast
polind =2.0D0, ! Polytropic index
radratio =0.35D0, ! Aspect ratio of the spherical shell
           =0.D0, ! Gravity profile
g0
           =0.D0,
g1
q2
            =1.00,
ktops
            =1, ! Entropy boundary condition
kbots
            =1.
ktopv
           =1, ! Mechanical boundary condition
           =1,
kbotv
&start_field
l_start_file=.FALSE.,
start_file ="rst_end.CJ3",
init_s1 =1919, ! Initial entropy perturbation pattern
          =0.01, ! Amplitude of the initial perturbation
amp_s1
&output_control
n_log_step =50, ! Store time series every 50 time steps
n\_graphs =1, ! 1 G\_\#.TAG file produced at the end of the run
n\_specs =5, ! 5 spectra produced during the run
n_rsts =1, ! 1 rst_end.TAG file produced at the end of the run
runid
           ="C.Jones bench",
&mantle
nRotMa
           =0
&inner core
sigma_ratio =0.d0,
nRotIC = 0,
```

This example might then be easily adapted to your desired configuration.

## 6.1 Grid namelist

This namelist defines the resolution of the computations. Keep in mind that **MagIC** is a 3D pseudo-spectral spherical shell code using Chebyshev polynomial expansions in the radial and spherical harmonic expansions in the angular directions.

#### 6.1.1 Outer Core

•  $n_r$  (default  $n_r$  max=33) is an integer which gives the number of grid points in the radial direction in the outer core ( $[r_i, r_o]$ ). It must be of the form 4 \* n + 1, where n is an integer.

**Note:** The possible values for  $n\_r\_max$  are thus: 17, 21, 25, 33, 37, 41, 49, 61, 65, 73? 81, 97, 101, 121, 129, 145, 161, 257, 401, 513, ...

• n\_cheb\_max (default n\_cheb\_max=31) is an integer which is the number of terms in the Chebyshev polynomial expansion to be used in the radial direction - the highest degree of Chebyshev polynomial used being n\_cheb\_max-1. Note that n\_cheb\_max <= n\_r\_max.

Note: Adopting n\_cheb\_max=n\_r\_max-2 is usually a good choice

- n\_phi\_tot (default n\_phi\_tot=192) is an integer which gives the number of longitudinal/azimuthal grid points. It has the following contraints:
  - n\_phi\_tot ' must be a multiple of minc (see below)
  - n\_phi\_tot/minc must be a multiple of 4
  - n\_phi\_tot must be a multiple of 16

**Note:** The possible values for  $n\_phi\_max$  are thus: 16, 32, 48, 64, 96, 128, 192, 256, 288? 320, 384, 400, 512, 576, 640, 768, 864, 1024, 1280, 1536, 1792, 2048, ...

#### 6.1.2 Inner Core

- $n_r_{ic}$  max (default  $n_r_{ic}$  max=17) is an integer which gives the number of grid points in the radial direction in the inner core ([0,  $r_i$ ]). It too, must be of the form 4\*n+1, where n is an integer.
- n\_cheb\_ic\_max (default n\_cheb\_ic\_max=15) is the number of terms in the Chebyshev polynomial expansion in the radial direction in the inner core. Only Chebyshev polynomials of even degrees are used in the expansion giving the highest degree used to be 2\*n\_cheb\_ic\_max-2. Note that here too, n\_cheb\_ic\_max <= n r max.

#### 6.1.3 Symmetry and aliasing

- minc (default minc=1) is an integer which gives the longitudinal symmetry. e.g. minc=n would give an n-fold rotational symmetry in the azimuthal direction. One can use this to reduce computational costs when the symmetry of the solution is known. The orders of the spherical harmonic expansion (m) are multiples of minc.
- nalias (default nalias=20) is an integer which determines antialiasing used in the spherical harmonic representation. Note that 20 <= nalias <= 30.

The number of grid points in latitude  $n\_theta\_max = n\_phi\_tot/2$ . The maximum degree  $(1\_max)$  and maximum order  $(m\_max)$  of the spherical harmonic expansion are determined by nalias:

```
l_max = (nalias * n_theta_max)/30
```

#### 6.2 Control namelist

This namelist defines the numerical parameters of the problem plus the variables that control and organize the run.

6.2. Control namelist 33

• mode (default mode=0) is an integer which controls the type of calculation performed.
---

mode=0	Self-consistent dynamo
mode=1	Convection
mode=2	Kinematic dynamo
mode=3	Magnetic decay modes
mode=4	Magneto convection
mode=5	Linear onset of convection
mode=6	Self-consistent dynamo, but with no Lorentz force
mode=7	Super-rotating inner core or mantle, no convection and no magnetic field
mode=8	Super-rotating inner core or mantle, no convection
mode=9	Super-rotating inner core or mantle, no convection and no Lorentz force
mode=10	Super-rotating inner core or mantle, no convection, no magnetic field, no Lorentz force and no
	advection

- tag (default tag="default") is a character string, used as an extension for all output files.
- n\_time\_steps (default n\_time\_steps=100) is an integer, the number of time steps to be performed.
- **tEND** (default *tEND=0.0*) is a real, which can be used to force the code to stop when :math:t=tEND. This is only used when t/=tEND.
- alpha (default alpha=0.5) is a real. This is the weight used for current time step in implicit time step.

#### 6.2.1 Default scales

• n\_tScale (default n\_tScale=0) is an integer, which determines the time scaling

n_tScale=0	Use viscous time scale.
n_tScale=1	Use magnetic time scale.
n_tScale=2	Use thermal time scale.

•  $n_lScale$  (default  $n_lScale=0$ ) is an integer which determines the reference length scale.

n_lScale=0	Use outer core.
n_lScale=1	Use total core.

• enscale (default enscale=1.0) is a real. This is the scaling for energies.

## 6.2.2 Update control

- l\_update\_v (default l\_update\_v=.true.) is a logical that specifies whether the velocity field should be time-stepped or not.
- l\_update\_b (default l\_update\_b=.true.) is a logical that specifies whether the magnetic field should be time-stepped or not.
- l\_update\_s (default l\_update\_s=.true.) is a logical that specifies whether the entropy/temperature should be time-stepped or not.

## 6.2.3 Time step control

A modified courant criteria including a modified Alfven-velocity is used to account for the magnetic field. The relative and absolute importance of flow and Alfven-velocity can be controlled by **courfac** and **alffac** respectively.

• **dtstart** (default *dtstart=0.0*) is a real, which is used as the initial time step if the starting solution is initialized (see below) and dtstart > 0.

- dtMax (default dtMax=1e-4) is a real. This is the maximum allowed time step  $\delta t$ . If  $\delta t >$  dtmax, the time step is decreased to at least dtmax (See routine  $dt\_courant$ ). Run is stopped if  $\delta t <$  dtmin and dtmin =  $10^{-6}$  dtmax.
- courfac (default courfac=2.5) is a real used to scale velocity in courant criteria.
- alffac (default alffac=1.0) is a real, used to scale Alfven-velocity in courant criteria.
- n\_cour\_step (default n\_cour\_step=10) is an integer. This is the number of time steps before consecutive checking of courant criteria. Note: the courant criteria is checked always after the time step has been changed if n\_cour\_step>0.

#### **6.2.4 Run time**

The total desired runtime (in human units and not in CPU units) can be specified with the three variables **runHours**, **runMinutes** and **runSeconds**.

- runHours (default runHours=0) is an integer that controls the number of run hours.
- runMinutes (default runMinutes=0) is an integer that controls the .
- runSeconds (default runSeconds=0) is an integer that controls the number of run hours.

Here is an example for a run of 23h30:

```
runHours = 23,
runMinutes = 30,
```

## 6.2.5 Hyperdiffusivity

Hyperdiffusion can be applied by multiplying the diffusion operators by a factor of the form

$$d(\ell) = 1 + D \left[ \frac{\ell + 1 - \ell_{hd}}{\ell_{max} + 1 - \ell_{hd}} \right]^{\beta}$$

for the spherical harmonic degrees  $\ell \geq \ell_{hd}$ .

- **difnu** (default difnu=0. 0) is a real. This is the amplitude D of the viscous hyperdiffusion.
- difkappa (default difkappa=0.0) is a real. This is the amplitude D of the thermal hyperdiffusion.
- **difeta** (default difeta=0.0) is a real. This is the amplitude D of the magnetic hyperdiffusion.
- **Idif** (default 1 dif=1) is an integer. This is the degree  $\ell_{hd}$  where hyperdiffusion starts to act.
- **Idifexp** (default 1 difexp=-1) is an integer. This is the exponent  $\beta$  of hyperdiffusion.

#### 6.2.6 Angular momentum correction

In case of the use of stress-free boundary conditions at both boundaries, it is safer to ensure that the angular momentum is correctly conserved. This can be enforced through the following input variables:

- l\_correct\_AMe (default l\_correct\_AMe=.false.) is a logical. This is used to correct the equatorial angular momentum.
- l\_correct\_AMz (default l\_correct\_AMz=.false.) is a logical. This is used to correct the axial angular momentum.

6.2. Control namelist 35

## 6.2.7 Mapping of the Gauss-Lobatto grid

Non-linear mapping function to concentrate/diperse grid points around a point inside the domain. For full description, see Bayliss and Turkel (1990). The function that re-distributes the collocation points is

$$r = \alpha_2 + \left\lceil \frac{\tan^{-1} \left( \lambda (r_{cheb} - x_0) \right)}{\alpha_1} \right\rceil ,$$

where the Gauss-Lobatto collocation points are

$$r_{cheb} = \cos\left(\frac{\pi(k-1)}{n_r}\right), \quad k = 1, 2, ..., n_r, \quad n_r = n_r max$$

and  $r \in [r_i, r_o]$ ,  $r_{cheb} \in [-1.0, 1.0]$ . The parameters to calculate r are

$$\lambda = \frac{\tan^{-1}(\alpha_1(1 - \alpha_2))}{1 - x_0}$$

$$x_0 = \frac{K - 1}{K + 1}$$

$$K = \frac{\tan^{-1}(\alpha_1(1 + \alpha_2))}{\tan^{-1}(\alpha_1(1 - \alpha_2))}$$

The coefficient  $\alpha_1$  determines the degree of concentration/dispersion of the grid points around  $r_{cheb} = \alpha_2$ . If  $\alpha_1$  is too high, the r function becomes nearly discontinuous. To avoid numerical problems,  $\alpha_1$  should remain close to unity.

- l\_newmap (default l\_newmap=.false.) is a logical. A radial mapping can be applied to the Chebyshev grid when l\_newmap is set to .true.. The radial profile of the mapping function is then stored during the initialisation of the code in the file *rNM.TAG*.
- alph1 (default alph1=2.0) is a real. This is a control parameter of the mapping function.
- alph2 (default alph2=0.0) is a real. This is a control parameter of the mapping function.

#### 6.2.8 Miscellaneous

• l\_non\_rot (default l\_non\_rot=.false.) is a logical. Use it when you want to do non-rotating numerical simulations.

# 6.3 Physical parameters namelist

This namelist contains all the appropriate relevant control physical parameters.

#### 6.3.1 Dimensionless control parameters

• ra (default ra=1.1e5) is a real. This the Rayleigh number expressed by

$$Ra = \frac{\alpha g_o \Delta T d^3}{\kappa \nu}$$

• ek (default ek=1e-3) is a real. This is the Ekman number expressed by

$$E = \frac{\nu}{\Omega d^2}$$

• pr (default pr=1.0) is a real. This is the Prandtl number expressed by

$$Pr = \frac{\nu}{\kappa}$$

• prmag (default prmag=5.0) is a real. This is the magnetic Prandtl number expressed by

$$Pm = \frac{\nu}{\lambda}$$

• radratio (default radratio=0.35) is a real. This is the ratio of the inner core radius  $r_i$  to the outer core radius  $r_o$ :

$$\eta = \frac{r_i}{r_o}$$

• strat (default strat=0.0) is a real. This is the number of density scale heights of the reference state:

$$N_{\rho} = \ln \frac{\tilde{\rho}(r_i)}{\tilde{\rho}(r_o)}$$

• **polind** (default polind=1.5) is a real. This is the polytropic index, which relates the background temperature to the background density:

$$\tilde{\rho} = \tilde{T}^m$$

**Warning:** Be careful: in its current version the code only handles **adiabatic** backgrounds, therefore changing polind physically means that the nature of the fluid (in particular its Grüneisen parameter) will change. For an ideal gas, it actually always follows  $m+1=\frac{\gamma-1}{\gamma}$ 

• l\_isothermal (default l\_isothermal=.false.) is a logical. When set to .true., makes the temperature background isothermal (i.e.  $\tilde{T}=cst$ .). In that case, the dissipation number Di vanishes and there is no viscous and Ohmic heating left. The only difference with the Boussinesq set of equations are thus restricted to the density background  $\tilde{\rho}$  and its radial derivatives that enters the viscous stress. This approximation is also called the zero Grüneisen parameter and was extensively explored by Denise Tortorella during her PhD.

#### 6.3.2 Heat sources and sinks

• epsc0 (default epsc0=0.0) is a real. This is the volumetric heat source  $\epsilon_0$  that enters the thermal equilibrium relation:

$$-\nabla \cdot \left(\tilde{\rho}\tilde{T}\nabla s\right) + \epsilon_0 f(r) = 0 \tag{6.1}$$

The radial function f(r) can be modified with the variable nVarEps that enters the same input namelist.

• **nVarEps** (default nVarEps=0) is an integer. This is used to modify the radial-dependence of the volumetric heat source, i.e. f(r) that enters equation (6.1).

nVarEps=0	Constant, i.e. $f(r) = \text{cst.}$ .
nVarEps=1	Proportional to density, i.e. $f(r) = \tilde{\rho}(r)$ .

#### 6.3.3 Realistic interior models

• interior\_model (default interior\_model="None") is a character string. This defines a polynomial fit of the density profile of the interior structure of several astrophysical objects. Possible options are "earth", "jupiter", "saturn" and "sun" (the naming is not case sensitive).

**Warning:** When interior\_model is defined the variables strat, polind, g0, g1 and g2 are not interpreted.

The subroutine radial gives the exact details of the implementation.

r\_cut\_model (default r\_cut\_model=0.98) is a real. This defines the cut-off radius of the reference model,
 i.e. the fluid domain is restricted to radii with r ≤ r<sub>cut</sub>.

The following input parameters will thus define a polynomial fit to the expected interior structure of Jupiter until 99% of Jupiter's radius (assumed here at the 1 bar level)

```
interior_model="JUP",
r_cut_model =0.99e0,
```

## 6.3.4 Gravity

The radial dependence of the gravity profile can be adjusted following

$$g(r) = g_0 + g_1 \frac{r}{r_o} + g_2 \left(\frac{r_o}{r}\right)^2 \tag{6.2}$$

The three following parameters are used to set this profile

- g0 (default g0=0) is the pre-factor of the constant part of the gravity profile, i.e.  $g_0$  in equation (6.2).
- g1 (default g1=1) is the pre-factor of the linear part of the gravity profile, i.e.  $g_1$  in equation (6.2).
- g2 (default g2=0) is the pre-factor of the  $1/r^2$  part of the gravity profile, i.e.  $g_2$  in equation (6.2).

## 6.3.5 Transport properties

• :difExp (default difExp=-0.5) is a real. This is the exponent that is used when nVarVisc=2, nVarDiff=2 or nVarCond=4.

#### **Electrical conductivity**

There are several electrical conductivity profiles implemented in the code that can be chosen with the nVarCond input variable. The following one corresponds to a constant electrical conductivity in the deep interior  $(r < r_m)$  and an exponential decay in the outer layer.

$$\sigma(r) = 1 + (\sigma_m - 1) \left(\frac{r - r_i}{r_m - r_i}\right)^a \quad \text{for} \quad r < r_m,$$

$$\sigma(r) = \sigma_m \exp\left[a\left(\frac{r - r_m}{r_m - r_i}\right) \frac{\sigma_m - 1}{\sigma_m}\right] \quad \text{for} \quad r \ge r_m.$$
(6.3)

• **nVarCond** (default *nVarCond=0*) is an integer. This is used to modify the radial-dependence of the electrical conductivity.

nVarCond=0	Constant electrical conductivity, i.e. $\sigma = \text{cst.}$	
nVarCond=1	$\sigma \propto \tanh[a(r-r_m)]$	
nVarCond=2	See equation (6.3).	
nVarCond=3	Magnetic diffusivity proportional to $1/\tilde{\rho}$ , i.e.	
	$\lambda = rac{ ilde{ ho}_i}{ ilde{ ho}}$	
nVarCond=2	Radial profile of the form:	
	$\lambda = \left(\frac{\tilde{\rho}(r)}{\tilde{\rho}_i}\right)^{\alpha}$	

- con\_RadRatio (default  $con_RadRatio=0.75$ ) is a real. This defines the transition radius  $r_m$  that enters equation (6.3).
- con\_DecRate (default con\_DecRate=9) is an integer. This defines the decay rate a that enters equation (6.3).
- con\_LambdaMatch (default  $con_LambdaMatch=0.6$ ) is a real. This is the value of the conductivity at the transition point  $\sigma_m$  that enters equation (6.3).
- con\_LambdaOut (default con\_LambdaOut=0.1) is a real. This is the value of the conduvity at the outer boundary. This parameter is only used when nVarCond=1.
- con\_FuncWidth (default con\_FuncWidth=0.25) is a real. This parameter is only used when nVarCond=1.
- r\_LCR (default  $r_LCR=2.0$ ) is a real.  $r_LCR$  possibly defines a low-conductivity region for  $r \ge r_{LCR}$ , in which the electrical conductivity vanishes, i.e.  $\lambda = 0$ .

#### Thermal diffusivity

• **nVarDiff** (default *nVarDiff=0*) is an integer. This is used to change the radial-dependence of the thermal diffusivity:

nVarDiff=0	Constant thermal diffusivity $\kappa$	
nVarDiff=1	Constant thermal conductivity, i.e.	
	$\kappa = rac{ ilde{ ho}_i}{ ilde{ ho}(r)}$	
nVarDiff=2	Radial profile of the form:	
	$\kappa = \left(rac{ ilde{ ho}(r)}{ ilde{ ho}_i} ight)^{lpha}$	
nVarDiff=3	polynomial-fit to an interior model of Jupiter	
nVarDiff=4	polynomial-fit to an interior model of the Earth liquid	
	core	

#### **Viscosity**

• nVarVisc (default nVarVisc=0) is an integer. This is used to change the radial-dependence of the viscosity:

nVarVisc=0	Constant kinematic viscosity $\nu$	
nVarVisc=1	Constant dynamic viscosity, i.e.	
	$ u = rac{ ilde{ ho}_o}{ ilde{ ho}(r)}$	
nVarVisc=2	Radial profile of the form:	
	$\nu = \left(\frac{\tilde{\rho}(r)}{\tilde{\rho}_i}\right)^{\alpha}$	

where  $\alpha$  is an exponent set by the namelist input variable difExp.

## 6.3.6 Anelastic liquid equations

Warning: This part is still work in progress. The input parameters here are likely to be changed in the future.

• **epsS** (default epsS=0.0) is a real. It controls the deviation to the adiabat. It can be related to the small parameter  $\epsilon$ :

$$\epsilon \simeq \frac{\Delta T}{T} \simeq \frac{\Delta s}{c_p}$$

- **cmbHflux** (default *cmbHflux=0.0*) is a real. This is the CMB heat flux that enters the calculation of the reference state of the liquid core of the Earth, when the anelastic liquid approximation is employed.
- **slopeStrat** (default slopeStrat=20.0) is a real. This parameter controls the transition between the convective layer and the stably-stratified layer below the CMB.

## 6.3.7 Boundary conditions

#### Thermal boundary conditions

• **ktops** (default *ktops=1*) is an integer to specify the outer boundary entropy (or temperature) boundary condition:

	Fixed entropy at outer boundary: $s(r_o) = s_{top}$
ktops=2	Fixed entropy flux at outer boundary: $\partial s(r_o)/\partial r = s_{top}$

- **kbots** (default ktops=1) is an integer to specify the inner boundary entropy (or temperature) boundary condition
- s\_top (default  $s_top=0 0 0.0 0.0$ ) is a real array of lateraly varying outer heat boundary conditions. Each four consecutive numbers are interpreted as follows:
  - 1. Spherical harmonic degree  $\ell$
  - 2. Spherical harmonic order m
  - 3. Real amplitude (cos contribution)
  - 4. Imaginary amplitude (sin contribution)

For example, if the boundary condition should be a combination of an  $(\ell = 1, m = 0)$  sherical harmonic with the amplitude 1 and an  $(\ell = 2, m = 1)$  spherical harmonic with the amplitude (0.5,0.5) the respective namelist entry could read:

 $s_{top} = 1, 0, 1.0, 0.0, 2, 1, 0.5, 0.5, ! The comas could be left away.$ 

- s\_bot (default  $s_bot=0 \ 0 \ 0.0 \ 0.0$ ) is a real array. This is the same as s\_top but for the bottom boundary.
- impS (default impS=0) is an integer. This is a flag to indicate if there is a localized entropy disturbance, imposed at the CMB. The number of these input boundary conditions is stored in n\_impS (the maximum allowed is 20), and it's given by the number of sCMB defined in the same namelist. The default value of impS is zero (no entropy disturbance). If it is set in the namelist for an integer greater than zero, then sCMB has to be also defined in the namelist, as shown below.
- sCMB (default sCMB=0.0 0.0 0.0 0.0) is a real array of CMB heat boundary conditions (similar to the case of s\_bot and s\_top). Each four consecutive numbers are interpreted as follows:
  - 1. Highest amplitude value of the entropy boundary condition, stored in array peakS(20). When impS<0, peakS is a relative amplitude in comparison to the  $(\ell = 0, m = 0)$  contribution (for example, the case s\_top= 0 0 -1 0).
  - 2.  $\theta$  coordinate (input has to be given in degrees), stored in array thetaS (20).
  - 3.  $\phi$  coordinate (input has to be given in degrees), stored in array phis (20).
  - 4. Angular width (input has to be given in degrees), stored in array widthS (20).

#### **Mechanical boundary conditions**

• **ktopv** (default ktopv=2) is an integer, which corresponds to the mechanical boundary condition for  $r=r_o$ .

ktopv=1	Stress-free outer boundary for $r=r_o$ :	
	$w_{\ell m}(r=r_o) = 0,  \frac{\partial}{\partial r} \left( \frac{1}{r^2 \tilde{\rho}} \frac{\partial w_{\ell m}}{\partial r} \right) = 0$	
	$\frac{\partial}{\partial r} \left( \frac{1}{r^2 \hat{\rho}} z_{\ell m} \right) = 0$	
ktopv=2	Rigid outer boundary for $r=r_o$ :	
	$w_{\ell m} = 0,  \frac{\partial w_{\ell m}}{\partial r} = 0,$ $z_{\ell m} = 0$	
	$z_{\ell m} = 0$	

• **kbotv** (default kbotv=2) is an integer, which corresponds to the mechanical boundary condition for  $r=r_i$ .

#### **Magnetic boundary conditions**

• **ktopb** (default ktopb=1) is an integer, which corresponds to the magnetic boundary condition for  $r=r_o$ .

ktopb=1	Insulating outer boundary:	
	$\frac{\partial b_{\ell m}}{\partial r} + \frac{\ell}{r} b_{\ell m} = 0,  \frac{\partial j_{\ell m}}{\partial r} = 0$	
ktopb=3	Finitely conducting mantle	
ktopb=4  Pseudo-vacuum outer boundary:		
	$\frac{\partial b_{\ell m}}{\partial r} = 0,  j_{\ell m} = 0$	

• <b>kbotb</b> (default <i>kbotb=</i> .	1) is an integer, which corresp	ponds to the magnetic boundar	y condition for $r = r_i$ .
---	---------------------------------	-------------------------------	-----------------------------

kbotb=1	Insulating inner boundary:
	$\frac{\partial b_{\ell m}}{\partial r} - \frac{\ell+1}{r} b_{\ell m} = 0,  \frac{\partial j_{\ell m}}{\partial r} = 0$
ktopb=2	Perfectly-conducting innner core:
	$b_{\ell m} = \frac{\partial b_{\ell m}}{\partial r} = 0,  \frac{\partial j_{\ell m}}{\partial r} = 0$
ktopb=3	Finitely conducting innner core
ktopb=4	Pseudo-vacuum outer boundary:
	$\frac{\partial b_{\ell m}}{\partial r} = 0,  j_{\ell m} = 0$

# **6.4 External Magnetic Field Namelist**

The namelist &B\_external provides options for imposing an external magnetic field.

## 6.4.1 Externally imposed magnetic field

• n\_imp (default  $n_imp = 0$ ) is an integer controlling the type of external field applied.

n_imp=0	No external magnetic field
n_imp=1	Follows idea of Uli Christensen of external field compensating internal field such that
	radial component of magnetic field vanishes at $r/r_{cmb} = rrMP$ where rrMP is the
	'magnetopause radius' input by the user (see below)
n_imp=2	Uniform axisymmetric magnetic field of geometry given by 1_imp (see below)
n_imp=3	Uniform axisymmetric magnetic field which changes direction according to the direc-
	tion of the axial dipole of the internal magnetic field
n_imp=4	Same as n_imp=3 but the amplitude of the external field is scaled to the amplitude
	of the axial dipole of the internal field
n_imp=7	External field depends on internal axial dipole through Special Heyner feedback func-
	tions

- **rrMP** (default *rrMP* = 0.0) is a real which gives the value of 'magnetopause radius'. In other words, it gives the radius (as a fraction of r\_cmb) at which the radial component of the magnetic field vanishes due to cancelling out of external and internal magnetic field components. Used only when n\_imp = 1.
- amp\_imp (default amp\_imp = 0.0) is a real which gives the amplitude of the external magnetic field.
- **expo\_imp** (default <code>expo\_imp = 0.0</code>) is a real which gives the exponent of dependence of external magnetic field on the axial dipole of the internal magnetic field. Used for n\_imp=7.
- bmax\_imp (default  $bmax_imp = 0.0$ ) is a real which gives the location of the maximum of the ratio of the poloidal potentials  $g_{ext}/g_{int}$ .
- l\_imp (default l\_imp = 1) is an integer which gives the geometry (degree of spherical harmonic) of the external magnetic field. The external field is always axisymmetric, hence m = 0 always. This option is used when n\_imp = 2, 3 or 4.

## 6.4.2 Current carrying loop

To simulate experiments, an external current carrying loop, concentric to the sphere and in the equatorial plane, has been implemented in the code. It's radius is fixed at a distance  $a=r_{cmb}/0.8$  to match conditions of the Maryland 3 metre experiment.

- l\_curr (default l\_curr = .false.) is a logical that controls switching on or off of the current carrying loop.
- amp\_curr (default amp\_curr = 0.0) is a real that gives the amplitude of magnetic field produced by the current carring loop.

**Warning:** Note that an external magnetic field is incompatible with a region of low conductivity inside the spherical shell (i.e, if  $r_LCR < r_cmb$ ). Thus, while imposing an external magnetic field, make sure  $r_LCR > r_cmb$  (which is the default case). For details on  $r_LCR$ , have a look at the section on *electrical conductivity* in the namelist for *physical parameters*.

## 6.5 Start field namelist

This namelist controls whether a start field from a previous solution should be used, or a specific field should be initialized.

## 6.5.1 Reading an input file of start fields

- l\_start\_file (default l\_start\_file=.false.) is a logical that controls whether the code should to read a file named start\_file or not.
- start\_file (default start\_file="no\_start\_file") is a character string. This is the name of the restart file.
- **inform** (default *inform=-1*) is an integer that can be used to specify the format of start\_file. This ensures possible backward compatibility with previous versions of the code. You shouldn't change this value except to read very old *rst\_end.TAG* files generated by older versions of MagIC.

inform=0	Oldest format used by U. Christensen	
inform=1	Newer format used by U. Christensen	
inform=2	Inner core introduced by J. Wicht	
inform=-1	Default format	

- scale\_s (default scale\_s=1.0) is a real. It can be possibly used to multiply the input entropy field from start\_file by a constant factor scale\_s.
- scale\_v (default scale\_v=1.0) is a real. It can be possibly used to multiply the input velocity field from start file by a constant factor scale v.
- scale\_b (default scale\_b=1.0) is a real. It can be possibly used to multiply the input magnetic field from start\_file by a constant factor scale\_b.
- **tipdipole** (default tipdipole=0.0) is a real that can be used to add non-axisymmetric disturbances to a start solution if non-axisymmetric parts have been lost due to mapping to a different symmetry. A  $(\ell=1, m=1)$  entropy term is added with:

$$s_{10}(r) = \text{tipdipole } \sin[\pi(r - r_i)]$$

If a magnetic field without an m=1 term is mapped into a field that permits this term, the code adds the respective poloidal field using the  $(\ell=1, m=0)$  poloidal magnetic field and scaling it with tipdipole.

• l\_reset\_t (default l\_reset\_t=.false.) is a logical that can be set to .true. in case one wants to reset the time of start file to zero.

## 6.5.2 Defining the starting conditions

#### Initialisation of entropy

The heat equation with possible heat sources and sinks given by  $epsc\theta$  is solved for the spherically-symmetric term  $(\ell=0,m=0)$  to get its radial dependence. In addition to this initial state, two other laterally varying terms can be initialized. Their radial dependence are assumed to follow:

$$s(r) = 1 - 2x^2 + 3x^4 - x^6,$$

where

$$x=2r-r_o-r_i$$
.

The initial perturbation is thus set to zero at both boundaries  $r_i$  and  $r_o$ , and reaches its maximum amplitude of amp\_s1 or amp\_s2 at the mid-shell radius  $r_i + 1/2$ .

- init\_s1 (default init\_s1=0) is an integer that controls the initial entropy. The following values are possible:
  - init\_s1=0: nothing is initialized
  - init\_s1<100: a random-noise of amplitude amp\_s1 is initialised. The subroutine initS in init\_fields.f90 gives the detail of this implementation.
  - init\_s1>100: initialisation of mode with the spherical harmonic order m given by the last two (or three) digits of init\_s1 and the spherical harmonic degree  $\ell$  given by the first two (or three) digits. Here are two examples:

```
init_s1 = 0707,
amp_s1 = 0.05,
```

will introduce a perturbation on the mode ( $\ell = 7, m = 7$ ) with an amplitude of 0.05.

```
init_s1 = 121121,
amp_s1 = 0.01,
```

will introduce a perturbation on the mode  $(\ell = 121, m = 121)$  with an amplitude of 0.01.

- amp s1 (default amp s1=0.0) is a real used to contol the amplitude of the perturbation defined by init s1.
- init\_s2 (default init\_s2=0) is an integer that controls a second spherical harmonic degee. It follows the same specifications as init\_s1.
- amp\_s2 (default amp\_s2=0.0) is a real used to contol the amplitude of the perturbation defined by init\_s2.

#### Initialisation of magnetic field

- init\_b1 (default init\_b1=0) is an integer that controls the initial magnetic field. The following values are possible:
  - init\_b1<0: random noise initialization of all  $(\ell, m)$  modes, except for  $(\ell = 0, m = 0)$ . The subroutine initB in the file init\_fields.f90 contains the details of the implementation.
  - init\_b1=0: nothing is initialized
  - init\_b1=1: diffusive toroidal field initialized. Mode determined by imagcon.

- init\_b1=2:  $(\ell=1, m=0)$  toroidal field with a maximum field strength of amp\_b1. The radial dependence is defined, such that the field vanishes at both the inner and outer boundaries. In case of an insulating inner core:  $t(r) \approx r \sin[\phi(r-r_o)]$ . In case of a conducting inner core:  $t(r) \approx r \sin[\pi(r/r_o)]$ .
- init\_b1=3:  $(\ell=1,m=0)$  poloidal field whose field strength is amp\_b1 at  $r=r_i$ . The radial dependence is chosen such that the current density j is independent of r:, i.e.  $\partial j/\partial r=0$ .  $(\ell=2,m=0)$  toroidal field with maximum strength amp\_b1.
- init\_b1=4:  $(\ell = 1, m = 0)$  poloidal field as if the core were an insulator (potential field). Field strength at  $r = r_i$  is again given by amp\_b1.
- init\_b1=5:  $(\ell=1, m=0)$  poloidal field with field strength amp\_b1 at  $r=r_i$ . The radial dependence is again defined by  $\partial j/\partial r=0$ .
- init\_b1=6:  $(\ell=1, m=0)$  poloidal field independend of r.
- init\_b1=7:  $(\ell=1,m=0)$  poloidal field which fulfills symmetry condition in inner core:  $b(r) \approx \left(\frac{r}{r_i}\right)^2 \left[1-\frac{3}{5}\left(\frac{r}{r_o}\right)^2\right]$ . The field strength is given by amp\_b1 at  $r=r_o$ .
- init\_b1=8: same poloidal field as for init\_b1=7. The toroidal field fulfills symmetry conditions in inner core and has a field strength of amp\_b1 at  $r=r_i$ :  $t(r) \approx \left(\frac{r}{r_i}\right)^3 \left[1-\left(\frac{r}{r_o}\right)^2\right]$ .
- init\_b1=9:  $(\ell=2, m=0)$  poloidal field, which is a potential field at the outer boundary.
- init\_b1=10: equatorial dipole only.
- init\_b1=11: axial and equatorial dipoles.
- init\_b1=21: toroidal field created by inner core rotation, equatorially symmetric  $(\ell=1, m=0)$ :  $t(r) = \text{ampb1} \left(\frac{r_i}{r}\right)^6$ . The field strength is given by amp\_b1 at  $r=r_i$ .
- init\_b1=22: toroidal field created by inner core rotation, equatorially antisymmetric ( $\ell=2, m=0$ ). Same radial function as for init\_b1=21.
- amp\_b1 (default amp\_b1=0.0) is a real used to contol the amplitude of the function defined by init\_b1.
- **imagcon** (default *imagcon=0*) is an integer, which determines the imposed magnetic field for magnetoconvection. The magnetic field is imposed at boundaries.
  - imagcon=0: no magneto-convection
  - imageon<0: axial poloidal dipole imposed at ICB with a maximum magnetic field strength amp\_b1.
  - imagcon=10:  $(\ell=2, m=0)$  toroidal field imposed at ICB and CMB with a maximum amplitude amp\_b1 at both boundaries.
  - imagcon=10:  $(\ell=2, m=0)$  toroidal field imposed at ICB and CMB with a maximum amplitude amp b1 at both boundaries.
  - imagcon=11: same as imagcon=10 but the maximum amplitude is now amp\_b1 at the ICB and -amp\_b1 at the CMB.
  - imageon=12:  $(\ell=1,m=0)$  toroidal field with a maximum amplitude of amp\_b1 at the ICB and the CMB
- tmagcon (tmagcon=0.0) is a real.

#### Initialisation of velocity field

- init\_v1 (default  $init\_v1=0$ ) is an integer that controls the initial velocity. The following values are possible:
  - init\_v1=0: nothing is initialized

- init\_v1=1: a differential rotation profile of the form

$$\Omega = \Omega_{ma} + 0.5\Omega_{ic} \quad \text{for} \quad s \le r_i$$
  
$$\Omega = \Omega_{ma} \quad \text{for} \quad s > r_i$$

where  $s = r \sin \theta$  is the cylindrical radius. This profile only makes sense when one studies spherical Couette flows.

- init\_v1=2: a differential rotation profile of the form  $\Omega = \frac{\text{ampv1}}{\sqrt{1+s^4}}$  is introduced.
- init\_v1>2: a random-noise of amplitude amp\_v1 is initialised. The subroutine initV in init\_fields.f90 gives the detail of this implementation.
- amp\_v1 (default amp\_v1=0.0) is a real used to contol the amplitude of the function defined by init\_v1.

# 6.6 Output control namelist

This namelist contains all the parameters that can be adjusted to control the outputs and diagnostics calculated by the code.

There are four different ways to control at which time step a specific output should be written. Outputs are generally distributed over the total calculation interval unless an output time interval is defined by a start time t\_start and a stop time t\_stop. If no t\_start is provided, the start time of the calculation is used. If no t\_stop is provided or t\_stop>t\_start the total calculation interval is assumed

1. **Prescribed number of outputs**. The outputs are distributed evenly over the total calculation interval so that the number of timesteps between two outputs is always the same, with the possible exception of the first interval. Last output is written for the last time step, and to compensate the interval before the first output may be longer. However, if t\_stop is provided, the outputs are distributed evenly over the interval [t\_stop, t\_start] with equal times intervals between them.

**Note:** These input variables are usually named with a pattern that follows  $n_{\text{outputName}}$ , for instance,  $n_{\text{graphs}}$ ,  $n_{\text{rsts}}$ ,  $n_{\text{specs}}$ ,  $n_{\text{logs}}$ , etc.

In case you want to make use of a specific time interval, the input variables follow a pattern of the form t\_outputName\_start, t\_outputName\_stop. For instance, t\_graph\_start, t\_graph\_stop, t\_log\_start, t\_log\_stop, t\_spec\_start, t\_spec\_stop, etc.

2. **User-defined interval between two outputs, given in number of time steps**. Again the last output is performed at the end of the run and a compensation may take place at the beginning.

**Note:** These input variables are usually named with a pattern that follows n\_outputName\_step, for instance, n\_graph\_step, n\_rst\_step, n\_spec\_step, n\_log\_step, n\_movie\_step, etc.

3. Defined time interval between two outputs.

**Note:** These input variables are usually named with a pattern that follows  $dt\_outputName$ , for instance,  $dt\_graph$ ,  $dt\_rst$ ,  $dt\_spec$ ,  $dt\_log$ ,  $dt\_movie$ , etc.

4. **User-defined times for output**. By default 5000 different times can be defined for each output type. This can be increased by increasing n\_time\_hits in the file output\_data.f90. While the first three possibilities can only be used alternatively, the fourth one can be employed in addition to one of the two others.

Note: These input variables are usually named with a pattern that follows t\_outputName, for instance,

```
t_graph, t_rst, t_spec, t_log, t_movie, etc.
```

An important parameter in this context is *l\_true\_time*. If this is set to .true., the time steps of the program are modified to meet a desired output time. This forces a recalculation of the inversion matricies and therefore requires some additional computing time. When l\_true\_time=.false., the values at the timestep closest to the desired output time are chosen. Since the timesteps are generally small, this option suffices for most applications.

• l\_true\_time (default l\_true\_time=.false.) is a logical. It causes the code to change time steps to exactly meet the requested output times.

The different possible outputs control parameters are then extensively described in the following pages:

#### Possible outputs

- 1. Control standard/common outputs
- 2. CMB and radial coefficients
- 3. Storage of potentials in spectral space
- 4. Torsional oscillations diagnostics
- 5. Additional possible diagnostics

## 6.6.1 Standard time-series outputs

The **log** outputs controls the output of all the default time series of the file: kinetic and magnetic energies (e\_kin.TAG, e\_mag\_oc.TAG and e\_mag\_ic.TAG files), dipole information (dipole.TAG file), rotation (rot.TAG) parameters (par.TAG) and various additional diagnostics (misc.TAG):

• n\_log\_step (default n\_log\_step=50) is an integer. This is the number of timesteps between two log outputs.

**Warning:** Be careful: when using too small  $n\_log\_step$ , the disk access will dramatically increases, thus decreasing the code performance.

- n\_logs (default  $n_1 \log s = 0$ ) is an integer. This is the number of log-information sets to be written.
- $t_{\log}$  (default  $t_{10g}=-1.0 -1.0 \dots$ ) is real array, which contains the times when log outputs are requested.
- dt log (default  $dt = 1 \circ q = 0$ . 0) is a real, which defines the time interval between log outputs.
- $t_{log\_start}$  (default  $t_{log\_start} = 0.0$ ) is a real, which defines the time to start writing log outputs.
- t\_log\_stop (default t\_log\_stop=0.0) is a real, which defines the time to stop writing log outputs.

## 6.6.2 Restart files

The **rst** outputs controls the output of restart files ( $rst\_t\_\#.TAG$ ) (i.e. check points in time from which the code could be restarted):

- n\_rst\_step (default n\_rst\_step=0) is an integer. This is the number of timesteps between two restart files.
- n\_rsts (default n\_rsts=1) is an integer. This is the number of restart files to be written.
- t\_rst (default t\_rst=-1.0 -1.0 ...) is real array, which contains the times when restart files are requested.
- **dt\_rst** (default \( dt\_rst=0.0 \)) is a real, which defines the time interval between restart files.
- t\_rst\_start (default t\_rst\_start=0.0) is a real, which defines the time to start writing restart files.

- t\_rst\_stop (default t\_rst\_stop=0.0) is a real, which defines the time to stop writing restart files.
- n\_stores (default n\_stores=0) is an integer. This is another way of requesting a certain number of restart files. However, instead of creating each time a new restart file, if n\_stores > n\_rsts the restart file is overwritten, which can possibly help saving some disk space.

**Warning:** The rst files can become quite big and writting them too frequently will slow down the code. Except for very special use, the default set up should be sufficient.

## 6.6.3 Graphic files

The **graph** outputs controls the output of graphic files  $(G_\#.TAG)$  which contain a snapshot the entropy, the velocity field and the magnetic fields:

- n\_graph\_step (default n\_graph\_step=0) is an integer. This is the number of timesteps between two graphic files.
- n\_graphs (default n\_graphs=1) is an integer. This is the number of graphic files to be written.
- **t\_graph** (default *t\_graph=-1.0 -1.0 ...*) is real array, which contains the times when graphic files are requested.
- **dt\_graph** (default \( dt\_graph=0.0 \)) is a real, which defines the time interval between graphic files.
- t\_graph\_start (default t\_graph\_start=0.0) is a real, which defines the time to start writing graphic files.
- $t_graph_stop$  (default  $t_graph_stop=0.0$ ) is a real, which defines the time to stop writing graphic files.

## 6.6.4 Spectra

The **spec** outputs controls the output of spectra: kinetic energy spectra (*kin\_spec\_#.TAG*), magnetic energy spectra (*mag\_spec\_#.TAG*) and thermal spectra (*T\_spec\_#.TAG*):

- n\_spec\_step (default n\_spec\_step=0) is an integer. This is the number of timesteps between two spectra.
- n\_specs (default n\_specs=0) is an integer. This is the number of spectra to be written.
- **t\_spec** (default *t\_spec=-1.0 -1.0 ...*) is real array, which contains the times when spectra are requested.
- **dt\_spec** (default  $dt\_spec=0.0$ ) is a real, which defines the time interval between spectra.
- t\_spec\_start (default t\_spec\_start=0.0) is a real, which defines the time to start writing spectra.
- t spec stop (default t spec stop=0.0) is a real, which defines the time to stop writing spectra.

## 6.6.5 Movie files

The **movie** outputs controls the output of movie files (\*\_mov.TAG).

#### Specific inputs

• l\_movie (default l\_movie=.false.) is a logical. It needs to be turned on to get movie computed.

Several movie-files can be produced during a run (it is now limited to 30 by the variable "n\_movies\_max" in the module movie). The movies are defined by a keyword determining the fields to be plotted and an expression

that determines the nature of movie (r-slice,  $\theta$ -slice,  $\phi$ -slice, etc.). The code searches this information in a character string provided for each movie. These strings are elements of the array movie:

• movie (default movie=' ', ' ', ...) is a character string array. It contains the description of the movies one wants to compute.

For example, to invoke a movie(file) that shows (stores) the radial magnetic component of the magnetic field at the CMB, you have to provide the line

```
movie(1)="Br CMB",
```

in the &output namelist. Here, Br is the keyword for the radial component of the magnetic field and CMB is the expression that defines the movie surface. If, in addition, a movie of the temperature field at the meridional slice phi=0 and a movie of the z-vorticity in the equatorial plane are desired, the following line have to be added:

```
movie(2)="Temp phi=0",
movie(3)="Vortz eq",
```

Note that the code does **not interpret spaces and ignores additional characters** that do not form a keyword or a surface definition. Thus, for example Br or Bradial are all interpreted as the same keyword. Furthermore, the interpretation is **not case-sensitive**. The following table gives the possible keywords for movie calculations and their corresponding physical meaning:

Keyword	Fields stored in movie file
Br[radial]	Radial component of the magnetic field $B_r$ .
Bt[heta]	Latitudinal component of the magnetic field $B_{\theta}$ .
Bp[hi]	Azimuthal component of the magnetic field $B_{\phi}$ .
Bh[orizontal]	The two horizontal components of the magnetic field.
Bs	Cylindrically radial component of the magnetic field $B_s$ .
Ba[ll]	All magnetic field components.
Fieldline[s] or FL	Axisymmetric poloidal field lines in a meridional cut.
AX[ISYMMETRIC]	Axisymmetric phi component of the magnetic field for $\phi = cst$ .
B or AB	
Vr[adial]	Radial component of the velocity field $u_r$ .
Vt[heta]	Latitudinal component of the velocity field $u_{\theta}$ .
Vp[hi]	Azimuthal component of the velocity field $u_{\phi}$ .
Vh[orizontal]	Horizontal velocity field, two components depending on the surface.
Va[11]	All velocity field components.
Streamline[s] or SL	Field lines of axisymmetric poloidal field for $\phi = cst$ .
AX[ISYMMETRIC]	Axisymmetric component of the velocity field for $\phi = cst$ .
V or AV	
Vz	Vertical component of the velocity at the equator + vertical component
	of the vorticity at the equator (closest point to equator).
Voz	Vertical component of the vorticity $\omega_z$ .
Vor	Radial component of the vorticity $\omega_r$ .
Vop	Azimuthal component of vorticity $\omega_{\phi}$
Tem[perature] or En-	Temperature/Entropy
tropy	
Entropy (or	Axisymmetric temperature/entropy field for $\phi = cst$ .
Tem[perature])	
AX[ISYMMETRIC]	
or AT	
Heat t[ransport]	Radial advection of temperature $u_r \frac{\partial s}{\partial r}$
HEATF	Conducting heat flux $\partial s/\partial r$
AX[iSYMMETRIC]	
	Continued on next page

Table 6.1 – continued from previous page

Keyword	Fields stored in movie file
FL Pro	Axisymmetric field line stretching.
FL Adv	
	Axisymmetric field line advection.
FL Dif	Axisymmetric field line diffusion.
AB Pro	Toroidal axisymmetric field production.
AB Dif	Toroidal axisymmetric field diffusion.
Br Pro	Production of radial magnetic field $B_r$ .
Br Adv	Advection of radial magnetic field $B_r$ .
Br Dif	Diffusion of radial magnetic field $B_r$ .
Jr	Radial component of the current $j_r$ .
Jr Pro	Production of radial current + $\Omega$ -effect.
Jr Adv	Advection of the radial component of the current $j_r$ .
Jr Dif	Diffusion of the radial component of the current $j_r$ .
Bz Pol	Poloidal part of vertical component of the magnetic field $B_z$ .
Bz Pol Pro	Production of the poloidal part of the vertical component of the mag-
	netic field $B_z$ .
Bz Pol Adv	Advection of the poloidal part of the vertical component of the magnetic
	field $B_z$ .
Bz Pol Dif	Diffusion of the poloidal part of the vertical component of the magnetic
	field $B_z$ .
Jz Tor	Toroidal part of the vertical component of the current $(j_z)$ .
Jz Tor Pro	Production of the toroidal part of the vertical component of the current
	$j_z$ .
Jz Tor Adv	Advection of the toroidal part of the vertical component of the current
	$j_z$ .
Jz Tor Dif	Diffusion of the toroidal part of the vertical component of the current
VE TOT DIT	$j_z$ .
Bp Tor	Toroidal part of the azimuthal component of the magnetic field $B_{\phi}$ .
Bp Tor Pro	Production of the toroidal part of the azimuthal component of the mag-
Dp 101110	netic field $B_{\phi}$ .
Bp Tor Adv	Advection of the toroidal part of the azimuthal component of the mag-
Dp for rav	netic field $B_{\phi}$ .
Bp Tor Dif	Diffusion of the toroidal part of the azimuthal component of the mag-
Dp for Dir	netic field $B_{\phi}$ .
HEL[ICITY]	Kinetic helicity $\mathcal{H} = \boldsymbol{u} \cdot (\boldsymbol{\nabla} \times \boldsymbol{u})$
AX[ISYMMETRIC	Axisymmetric component of the kinetic helicity.
HELICITY] or	Available component of the killette hencity.
AHEL	
Bt Tor	Toroidal component of the latitudinal component of the magnetic field
Dt IOI	$B_{\theta}$ .
Pot Tor	Toroidal potential.
Pol Fieldlines	Poloidal fieldlines.
Br Shear	Azimuthal shear of the radial component of the magnetic field $B_r$
l .	
Lorentz[force] or LF	Lorentz force (only $\phi$ -component).
Br Inv	Inverse field apperance at CMB.

The following table gives the possible surface expression for movie calculations and their corresponding physical meaning:

Surface expression	Definition
CMB	Core-mantle boundary
Surface	Earth surface
EQ[uatot]	Equatorial plane
r=radius	Radial cut at r=radius with radius given in units of the outer core radius.
theta=colat	Latitudinal cut at theta=colat given in degrees
phi=phiSlice	Azimuthal cut ath phi=phiSlice given in degrees.
AX[isymmetric]	Axisymmetric quantity in an azimuthal plane
3D	3D array

Here is an additional example of the possible combinations to build your desired movie files.

```
l_movie = .true.,
movie(1) = "Br CMB",
movie(2) = "Vr EQ",
movie(3) = "Vortr r=0.8",
movie(4) = "Bp theta=45",
movie(5) = "Vp phi=10",
movie(6) = "entropy AX",
movie(7) = "vr 3D",
```

#### **Standard inputs**

- n\_movie\_step (default n\_movie\_step=0) is an integer. This is the number of timesteps between two movie outputs.
- n\_movies (default n\_movies=1) is an integer. This is the number of movie outputs to be written.
- t\_movie (default t\_movie=-1.0 -1.0 ...) is real array, which contains the times when movie outputs are requested.
- dt movie (default dt movie=0.0) is a real, which defines the time interval between movie outputs.
- t\_movie\_start (default t\_movie\_start=0.0) is a real, which defines the time to start writing movie outputs.
- t\_movie\_stop (default t\_movie\_stop=0.0) is a real, which defines the time to stop writing movie outputs.

## 6.6.6 Field Averages

The code can perform on-the-fly time-averaging of entropy, velocity field and magnetic field. Respective graphic output and spectra are written into the corresponding files (with *G\_ave.TAG*, *kin\_spec\_ave.TAG*, *mag\_spec\_ave.TAG*). The time-averaged energies are written into the *log.TAG* file.

• l\_average (default l\_average=.false.) is a logical, which enables the time-averaging of fields when set to .true..

**Warning:** Time-averaging has a large memory imprint as it requires the storage of 3-D arrays. Be careful, when using large truncations.

## 6.6.7 Poloidal magnetic field potential at CMB

The **cmb** outputs controls the output of poloidal field potential coefficients at the CMB  $b_{\ell m}(r=r_o)$ :  $B\_coeff\_cmb.TAG$  up to a maximum spherical harmonic degree  $1\_max\_cmb$ .

Note: This calculation is only enabled when 1 cmb field=.true. or when 1 dt cmb field=.true..

#### **Specific inputs**

- l\_cmb\_field (default l\_cmb\_field=.false.) is a logical. It needs to be turned on to get cmb files computed.
- l\_dt\_cmb\_field (default l\_dt\_cmb\_field=.false.) is a logical. When set to .true., it allows the calculation of the secular variation of the magnetic field at the CMB.
- l\_max\_cmb (default 1\_max\_cmb=14) is an integer. This is the maximum spherical harmonic degree  $\ell$  stored in B\_coeff\_cmb.TAG, i.e. only  $\ell \leq \ell_{maxcmb}$  are stored. For example, the following input parameter means that the B\_coeff\_cmb.TAG file is stored up to a spherical harmonic degree of  $\ell$ :

```
l_cmb_field = .true.,
l_max_cmb = 20,
```

#### **Standard inputs**

- n\_cmb\_step (default  $n_cmb_step=0$ ) is an integer. This is the number of timesteps between two cmb outputs.
- n\_cmbs (default n\_cmbs=0) is an integer. This is the number of cmb outputs to be written.
- t\_cmb (default t\_cmb=-1.0 -1.0 ...) is real array, which contains the times when cmb outputs are requested.
- **dt\_cmb** (default \( dt\_\_cmb=0 \). (0) is a real, which defines the time interval between cmb outputs.
- $t_{cmb\_start}$  (default  $t_{cmb\_start}=0.0$ ) is a real, which defines the time to start writing cmb outputs.
- t\_cmb\_stop (default t\_cmb\_stop=0.0) is a real, which defines the time to stop writing cmb outputs.

## 6.6.8 Poloidal and toroidal potentials at several depths

The coeff\_r# outputs controls the output of the poloidal and toroidal potential coefficients at several depths up to a maximum spherical harmonic degree  $l_{max_r}$ . The files  $B_{coeff_r\#.TAG}$  and  $V_{coeff_r\#.TAG}$  are written when  $l_{r_field=.true.}$ . The file  $T_{coeff_r\#.TAG}$  is written when  $l_{r_field=.true.}$ 

**Note:** This calculation is **only** enabled when <code>l\_r\_field=.true</code>. or when <code>l\_r\_fieldT=.true</code>..

#### Specific inputs

- l\_r\_field (default l\_r\_field=.false.) is a logical. It needs to be turned on to get r\_field files computed.
- l\_r\_fieldT (default l\_r\_fieldT=.false.) is a logical. When set to .true., the thermal field is also stored in a file named T\_coeff\_r\*.TAG.
- l\_max\_r (default l\_max\_r=l\_max) is an integer. This is the maximum spherical harmonic degree  $\ell$  stored in the r\_field file, i.e. only  $\ell \leq \ell_{maxcmb}$  are stored.

There are two ways to specify the radial grid points where you want to store the  $[B|V|T]\_coeff\_r\#$ . TAG files. You can specify a stepping  $n\_r\_step$ : in that case 5 coeff $\_r\#$ . TAG files will be stored at 5 different radial levels every  $n\_r\_step$  grid point:

```
l_r_field = .true.,
n_r_step = 6,
l_max_r = 30,
```

This will produces 5 files that contain the poloidal and toroidal potentials up to spherical harmonic degree  $\ell = 30$ :

- [B|V|T]\_coeff\_r1.TAG corresponds to the radial grid point with the index nR=6.
- [B|V|T]\_coeff\_r2.TAG to nR=12.
- [B|V|T]\_coeff\_r3.TAG to nR=18.
- [B|V|T]\_coeff\_r4.TAG to nR=24.
- [B|V|T]\_coeff\_r5.TAG to nR=30.
- $n_r$ step (default  $n_r$ step=2) is an integer. This specifies the stepping between two consecutive [B|V|T]coeff\_r#.TAG files.

Alternatively, the input array n\_r\_array can be used to specify the radial grid points you exactly want to store:

```
l_r_field = .true.,
n_r_array = 8, 24, 47,
l_max_r = 10,
```

This will produces 3 files that contain the poloidal and toroidal potentials up to spherical harmonic degree  $\ell = 10$ :

- [B|V|T]\_coeff\_r1.TAG corresponds to the radial grid point with the index nR=8.
- [B|V|T]\_coeff\_r2.TAG to nR=24.
- [B|V|T]\_coeff\_r3.TAG to nR=47.
- n\_r\_array (default n\_r\_array=0 0 0 ...) a an integer array. You can specify the radial grid points (starting from n\_r\_cmb=1) where you want to store the coefficients.

#### Standard inputs

- $n_r_{field\_step}$  (default  $n_r_{field\_step=0}$ ) is an integer. This is the number of timesteps between two  $r_{field\_outputs}$ .
- n\_r\_fields (default n\_r\_fields=0) is an integer. This is the number of r\_field outputs to be written.
- t\_r\_field (default t\_r\_field=-1.0 -1.0 ...) is real array, which contains the times when r\_field outputs are requested.
- $dt_r_{field}$  (default  $dt_r_{field}=0.0$ ) is a real, which defines the time interval between  $r_{field}$  outputs.
- t\_r\_field\_start (default t\_r\_field\_start=0.0) is a real, which defines the time to start writing r\_field outputs.
- t\_r\_field\_stop (default t\_r\_field\_stop=0.0) is a real, which defines the time to stop writing r\_field outputs.

# 6.6.9 Poloidal and toroidal potentials in spectral and Chebyshev space

The [VIBIT]pot outputs controls the output of potential files (Vpot\_#.TAG, Bpot\_#.TAG and Tpot\_#.TAG). These are files that contain the poloidal and toroidal flow and magnetic field potentials (and entropy/temperature) written in spectral and Chebyshev spaces (for instance w (lm\_max, n\_cheb\_max)). These files can be pretty useful since

they can be possibly used to reconstruct any quantity in the spectral space or in the physical space you may be interested in.

#### **Specific inputs**

They are two ways to store those files. The first option is to use <code>l\_storePot=.true</code>. and the corresponding time control parameters (<code>n\_pot\_step</code>, <code>t\_pot</code>, <code>n\_pots</code>, etc.). In that case the three files <code>Vpot\_#.TAG</code>, <code>Bpot\_#.TAG</code> and <code>Tpot\_#.TAG</code> will be stored. The following example will create new <code>Vpot\_#.TAG</code>, <code>Bpot\_#.TAG</code> and <code>Tpot\_#.TAG</code> files every 1000 time steps:

```
l_storePot = .true.,
n_pot_step = 1000,
```

• **l\_storePot** (default *l\_storePot=.false.*) is a logical. It needs to be turned on to store all the potentials in three different files: *Vpot\_#.TAG*, *Bpot\_#.TAG* and *Tpot\_#.TAG*.

The second option is control separately the writing of the three files using the three logicals <code>l\_storeVpot</code>, <code>l\_storeBpot</code> and <code>l\_storeTpot</code> and their corresponding time control parameters. The following example wrill create a new <code>Vpot\_#.TAG</code> file every 1000 time steps and a new <code>Bpot\_#.TAG</code> file every 3000 time steps (no <code>Tpot\_#.TAG</code> files are stored in that case):

```
l_storeVpot = .true.,
n_Vpot_step = 1000,
l_storeBpot = .true.,
n_Bpot_step = 3000,
l_storeTpot = .false.,
```

- **l\_storeVpot** (default *l\_storeVpot=.false.*) is a logical. It needs to be turned on to store the flow poloidal and toroidal potentials. It then writes the *Vpot\_#.TAG* file.
- **l\_storeBpot** (default *l\_storeBpot=.false.*) is a logical. It needs to be turned on to store the magnetic field poloidal and toroidal potentials. It then writes the *Bpot\_#.TAG* file.
- **l\_storeTpot** (default *l\_storeTpot=.false.*) is a logical. It needs to be turned on to store the entropy. It then writes the *Tpot\_#.TAG* file.

#### Standard inputs

- n\_pot\_step (default  $n_pot_step=0$ ) is an integer. This is the number of timesteps between two [V|B|P] pot outputs.
- **n\_pots** (default  $n_{pots}=1$ ) is an integer. This is the number of [V|B|P] pot outputs to be written.
- t\_pot (default  $t_pot = -1.0 -1.0 \dots$ ) is real array, which contains the times when [V|B|P]pot outputs are requested.
- **dt\_pot** (default  $dt_pot=0.0$ ) is a real, which defines the time interval between two [V|B|P] pot outputs.
- t\_pot\_start (default t\_pot\_start=0.0) is a real, which defines the time to start writing [V|B|P]pot outputs.
- t\_pot\_stop (default t\_pot\_stop=0.0) is a real, which defines the time to stop writing [V|B|P]pot outputs.
- n\_Vpot\_step (default n\_Vpot\_step=0) is an integer. This is the number of timesteps between two Vpot outputs.
- $n_V$ pots (default  $n_V$ pots=1) is an integer. This is the number of Vpot outputs to be written.

- t\_Vpot (default t\_Vpot=-1.0 -1.0 ...) is real array, which contains the times when Vpot outputs are requested.
- **dt\_Vpot** (default \( dt\_\)Vpot=0.0) is a real, which defines the time interval between Vpot outputs.
- t\_Vpot\_start (default t\_Vpot\_start=0.0) is a real, which defines the time to start writing Vpot outputs.
- t\_Vpot\_stop (default t\_Vpot\_stop=0.0) is a real, which defines the time to stop writing Vpot outputs.
- n\_Bpot\_step (default n\_Bpot\_step=0) is an integer. This is the number of timesteps between two Bpot outputs.
- n\_Bpots (default n\_Bpots=1) is an integer. This is the number of Bpot outputs to be written.
- t\_Bpot (default t\_Bpot=-1.0 -1.0 ...) is real array, which contains the times when Bpot outputs are requested.
- **dt\_Bpot** (default  $dt_Bpot=0.0$ ) is a real, which defines the time interval between Bpot outputs.
- t\_Bpot\_start (default t\_Bpot\_start=0.0) is a real, which defines the time to start writing Bpot outputs.
- $t_Bpot_stop$  (default  $t_Bpot_stop=0.0$ ) is a real, which defines the time to stop writing Bpot outputs.
- n\_Tpot\_step (default n\_Tpot\_step=0) is an integer. This is the number of timesteps between two Tpot outputs.
- n\_Tpots (default n\_Tpots=1) is an integer. This is the number of Tpot outputs to be written.
- t\_Tpot (default t\_Tpot=-1.0 -1.0 ...) is real array, which contains the times when Tpot outputs are requested.
- **dt\_Tpot** (default  $dt_Tpot = 0.0$ ) is a real, which defines the time interval between Tpot outputs.
- t\_Tpot\_start (default t\_Tpot\_start=0.0) is a real, which defines the time to start writing Tpot outputs.
- t\_Tpot\_stop (default  $t_Tpot_stop=0.0$ ) is a real, which defines the time to stop writing Tpot outputs.

#### 6.6.10 Torsional oscillations (TO)

#### **Specific inputs**

- **l\_TO** (default *l\_TO=.false.*) is a logical. It needs to be turned on to compute the torsional oscillations diagnostics (TO) computed.
- **1\_TOmovie** (default 1\_TOmovie=.false) is a logical. It needs to be turned on to store the TO\_movie.TAG files.
- **sDens** (default *sDens=1*.0) is a float. It gives the relative point density of the cylindrical grid (in the radial direction).
- **zDens** (default *zDens=1*.0) is a float. It gives the relative point density of the cylindrical grid (in the vertical direction).

#### Standard inputs

- n\_TO\_step (default n\_TO\_step=0) is an integer. This is the number of timesteps between two TO outputs.
- n\_TOs (default n\_TOs=1) is an integer. This is the number of TO outputs to be written.
- $\mathbf{t_T}$ **TO** (default  $t_T$ 0=-1.0 -1.0 ...) is real array, which contains the times when TO outputs are requested.
- $dt_TO$  (default  $dt_TO=0$ .0) is a real, which defines the time interval between TO outputs.

- t\_TO\_start (default t\_TO\_start=0.0) is a real, which defines the time to start writing TO outputs.
- t\_TO\_stop (default t\_TO\_stop=0.0) is a real, which defines the time to stop writing TO outputs.
- n\_TOZ\_step (default  $n_TOZ_step=0$ ) is an integer. This is the number of timesteps between two TO outputs.
- **n\_TOZs** (default  $n_TOZs=1$ ) is an integer. This is the number of TO outputs to be written.
- t\_TOZ (default t\_TOZ=-1.0 -1.0 ...) is real array, which contains the times when TO outputs are requested.
- **dt\_TOZ** (default  $dt_TOZ = 0.0$ ) is a real, which defines the time interval between TO outputs.
- t\_TOZ\_start (default t\_TOZ\_start=0.0) is a real, which defines the time to start writing TO outputs.
- t\_TOZ\_stop (default t\_TOZ\_stop=0.0) is a real, which defines the time to stop writing TO outputs.
- n\_TOmovie\_step (default n\_TOmovie\_step=0) is an integer. This is the number of timesteps between two TO\_mov outputs.
- n\_TOmovie\_frames (default n\_TOmovies=1) is an integer. This is the number of TO\_mov outputs to be written.
- t\_TOmovie (default t\_TOmovie=-1.0 -1.0 ...) is real array, which contains the times when TO\_mov outputs are requested.
- **dt\_TOmovie** (default dt\_TOmovie=0.0) is a real, which defines the time interval between TO\_mov outputs.
- t\_TOmovie\_start (default t\_TOmovie\_start=0.0) is a real, which defines the time to start writing TO\_mov outputs.
- t\_TOmovie\_stop (default t\_TOmovie\_stop=0.0) is a real, which defines the time to stop writing TO\_mov outputs.

#### 6.6.11 RMS force balance

**Warning:** The RMS calculation is actually wrong in the current version. This needs again to be ported from MagIC 3.44. The RMS contributions to the induction equation are correct, though. A ticket has been opened on github regarding this issue: https://github.com/magic-sph/magic/issues/1

The code can compute the RMS of the force balance and the induction equation.

- **l\_RMS** (default *l\_RMS=.false.*) is a logical, which enables the calculation of RMS force balance, when set to .true.. The outputs are stored in the *dtVrms.TAG*, *dtBrms.TAG* and *dtDrms.TAG* files.
- l\_RMStest (default l\_RMStest=.false.) is a logical. This is a debug flag to check the consistency of the RMS calculation.
- rCut (default rCut=0.075) is a float. This is the thickness of the layer which is left out at both boundaries for the RMS calculation. rCut=0.075 actually means that 7.5% below the CMB and above the ICB are disregarded in the force balance calculation.
- **rDea** (default *rDea=0.0*) is a float. This controls the dealiasing in RMS calculations. rDea=0.1 means that the highest 10% of the Chebyshev modes are set to zero.

## 6.6.12 Additional possible diagnostics

#### Geostrophy

- l\_par (default l\_par=.false.) is a logical. When set to .true., this logical enables additional calculations (for instance the degree of geostrophy). The details of these calculations can be found in the subroutine getEgeos in the Egeos.f90 file. These quantities are then stored in the columns 10-16 of the misc.TAG file.
- l\_corrMov (default l\_corrMov=.false.) is a logical. When set to .true., this logical enables the calculation of a movie file that stores North/South correlation in the CVorz mov.TAG file.

#### **Helicity**

• l\_hel (default l\_hel=.false.) is a logical. When set to .true., this logical enables the calculation of helicity (RMS, northern and southern hemisphere, etc.). The outputs are stored in the columns 6-9 of the *misc.TAG* file.

#### **Power budget**

• l\_power (default l\_power.false.) is a logical. When set to .true., this logical enables the calculation of input and output power (buoyancy, viscous and ohmic dissipations, torques). The time series are stored in power.TAG and dtE.TAG and the time-averaged radial profiles in powerR.TAG.

#### **Angular momentum**

• **l\_AM** (default *l\_AM=.false.*) is a logical. When set to .true., this logical enables the calculation of angular momentum. The time series are stored in *AM.TAG*.

#### **Drift rates**

• l\_drift (default l\_drift=.false.) is a logical. When set to .true., this logical enables the storage of some selected coefficients to allow the calculation of the drift rate. The time series are stored in drift[V|B][DQ].TAG.

#### Inertial modes

• l\_iner (default l\_iner=.false.) is a logical. When set to .true., this logical enables the storage of some selected  $w(\ell,m)$  at mid-shell (stored in *inerP.TAG*) and  $z(\ell,m)$  at mid-shell (stored in *inerT.TAG*). Those files can be further used to identify inertial modes.

#### Radial spectra

- l\_rMagSpec (default l\_rMagSpec=.false) is a logical. When set to .true., the magnetic spectra for the first 6 spherical harmonic degree  $\ell$  for all radii are stored at times of log ouputs. This produces the unformatted fortran files rBrSpec.TAG and rBpSpec.TAG.
- 1\_DTrMagSpec (default 1\_DTrMagSpec=.false) is a logical. When set to .true., the magnetic spectra of the magnetic field production terms for the first 6 spherical harmonic degree  $\ell$  for all radii are stored at times of log ouputs. This produces the unformatted fortran files rBrProSpec.TAG, rBrAdvSpec.TAG, rBrDifSpec.TAG, rBpDifSpec.TAG, rBpDifSpec.TAG and rBpDynSpec.TAG. All those files have exactly the same format as the rBrSpec.TAG.

#### **Heat transport**

• l\_fluxProfs (default l\_fluxProfs=.false.) is a logical. When set to .true., this logical enables the calculation of time-averaged radial heat flux profiles (conductive flux, convective flux, kinetic flux, viscous flux, Poynting flux and resistive flux). The time-averaged radial profiles are stored in the fluxesR.TAG file.

#### **Boundary layer analysis**

• l\_viscBcCalc (default l\_viscBcCalc=.false.) is a logical. When set to .true., this logical enables the calculation of time-averaged radial profiles that can be further use to determine the viscous and thermal boundary layer thicknesses: temperature, temperature variance, horizontal velocity, etc. The time-averaged radial profiles are stored in the bLayersR.TAG file.

#### Parallel/perpendicular decomposition

• l\_perpPar (default l\_perpPar=.false.) is a logical. When set to .true., this logical enables the decomposition of kinetic energy into components parallel and perpendicular to the rotation axis. The time series are stored in perpPar.TAG and the time-averaged radial profiles in perpParR.TAG.

#### **Potential vorticity**

• l\_PV (default 1\_PV=.false.) is a logical. When set to .true., this logical enables some potential vorticity diagnostics. At the end of the run, the results are stored in the the files PVZ.TAG and Vcy.TAG.

## 6.6.13 Generic options

- **l\_save\_out** (default *l\_save\_out=.false.*) is a logical. When set to .true., the diagnostic files will be safely opened and closed before and after any outputs. When set to .false., the diagnostic files will be opened before the first iteration timestep and close at the end of the run. This may cost some computing time, but guarantees that only minimal information is lost in case of a crash.
- IVerbose (default *lVerbose=.false.*) is a logical. When set to .true., the code displays a lot of debugging informations.

Warning: Never set lVerbose to .true. for a production run!

• **runid** (default, runid="MAGIC default run") is a character string. This can be used to briefly describe your run. This information is then for instance stored in the header of the graphic files.

## 6.7 Mantle and Inner Core Namelists

#### 6.7.1 Mantle Namelist

This namelist defines mantle properties

- conductance\_ma (default conductance\_ma=0.0) is a real that defines the conductance (dimensionless) of the mantle.
- **nRotMa** (default *nRotMa=0*) is an integer that defines the rotation of the mantle:

nRotMa=-1	Mantle rotates with prescribed rate (see omega_ma1 and omega_ma2 below)
nRotMa=0	Fixed, non-rotating mantle
nRotMa=1	Mantle rotates according to torques

- **rho\_ratio\_ma** (default *rho\_ratio\_ma=1*) is a real which gives the density of the mantle in terms of that of the outer core.
- omega\_ma1 (default omega\_ma1=0.0) is a real which defines a mantle rotation rate (used when nRotMa=0).
- omegaOsz\_ma1 (default omegaOsz\_ma1=0.0) is a real which prescribes the oscillation frequency of the mantle rotation rate. In this case, omega ma1 is the amplitude of the oscillation.
- tShift\_ma1 (default tShift\_ma1=0.0) is a real which defines the time shift of the mantle rotation rate omega\_ma1.
- omega\_ma2 (default omega\_ma2=0.0) is a real which defines a second mantle rotation rate.
- omegaOsz\_ma2 (default omegaOsz\_ma2=0.0) is a real which defines the oscillation frequency of the second mantle rotation rate omega\_ma2.
- tShift\_ma2 (default tShift\_ma2=0.0) is a real which defines the time shift for omega\_ma2.

The resultant prescribed mantle rotation rate is computed as:

```
omega_ma = omega_ma1*cos(omegaOsz_ma1*(time+tShift_ma1)) + &
    omega_ma2*cos(omegaOsz_ma2*(time+tShift_ma2))
```

#### 6.7.2 Inner Core Namelist

This namelist defines properties of the inner core

- **sigma\_ratio** (default *sigma\_ratio=0.0*) is a real that defines the conductivity of the inner core with respect to the value of the outer core. sigma\_ratio=0 thus corresponds to a non-conducting inner core.
- **nRotIc** (default *nRotIc=0*) is an integer that defines the rotation of the inner core. Behaves the same way as *nRotMa* (above).
- **rho\_ratio\_ic** (default rho\_ratio\_ic=1.0) is a real which defines the density of the inner core in terms of that of the outer core.
- **BIC** (default BIC=0.0) is a real which gives the imposed dipole field strength at the Inner Core Boundary. Having BIC > 0 implies that the inner core acts as a dipole magnet as implemented in the DTS experiment at Grenoble, France.
- Variables prescribing rotation rate of inner core The following variables are used to prescribe rotation rate of the inner core. They behave in the same way as the corresponding variables for the mantle. They are used only when nRotIC=0.

```
omega_ic1 (default omega_ic1=0.0)
omegaOsz_ic1 (default omegaOsz_ic1=0.0)
tShift_ic1 (default tShift_ic1=0.0)
omega_ic2 (default omega_ic2=0.0)
omegaOsz_ic2 (default omegaOsz_ic2=0.0)
```

- tShift\_ic2 (default tShift\_ic2=0.0)

As with the mantle, the resultant prescribed rotation rate for the inner core is computed as:

# INTERACTIVE COMMUNICATION WITH THE CODE USING SIGNAL. TAG

It is possible to interactively communicate with the MagIC code **during a run**, using a file which is systematically created when the simulation starts, called **signal.TAG**. By default, this file contains only the word NOT and does nothing to the simulation. Replacing NOT by one of the following allowed keywords will have some influence on the outputs or possibly force the code to terminate its execution:

- **END**: Changing the word NOT to END will cause the code to finish after the current time step and write all the outputs as if it was programmed to finish at that time from the start. This will thus normally produce the *rst\_end.TAG* file that will possibly allow you to continue this run later at your convenience.
- **GRA**: Changing the word NOT to GRA will cause the code to produce a graphic ouptut file *G\_#.TAG*. The keyword will be automatically restored to NOT once the graphic file has been produced.
- **RST**: Changing the word NOT to RST will cause the code to produce a restart file *rst\_t#.TAG*. The keyword will then be restored to NOT once the restart file has been written.
- **SPE**: Changing the word NOT to SPE will cause the code to produce spectra *kin\_spec\_#.TAG* (and possibly *mag\_spec\_#.TAG* and *T\_spec\_#.TAG* <*secTSpecFile>* depending if the run is magnetic or not, or if it solves a temperature/entropy equation). Once the spectra files have been written, the keyword will be automatically replaced by NOT.

**Note:** Those keywords are **case-insensitive**.

Instead of editing the file with your favorite editor to specify the requested keyword, we recommand using instead the shell command echo to avoid some possible crash during the code execution when writing into the signal.TAG file. For instance, if you want a *graphic output file*, just use the following command (adapted to your current *TAG*):

\$ echo GRA > signal.TAG

## **OUTPUT FILES**

While some information of a run is written into STDOUT to monitor its progress, most outputs are printed into dedicated files identified by the chosen *TAG* extension. These files can be parsed and analysed using the *python classes*. The following pages describe the content and the structure of the different type of output files:

- 1. Most of the information found in STDOUT is also written to the **log-file** called *log.TAG*. In addition, this file contains all input parameters, truncation, information on other output files, and some results like the time averaged energies (when *l\_average=.true.*).
- 2. There are several ascii files that contain the **time-evolution of integrated quantities** (energies, heat fluxes, rotation rate, Reynolds numbers, etc.) that are systematically produced:
  - Kinetic energies: *e\_kin.TAG*,
  - Magnetic energies: e\_mag\_oc.TAG and e\_mag\_ic.TAG,
  - Rotation rates: rot. TAG,
  - Informations about the dipolar component of the magnetic field: dipole.TAG,
  - Diagnostic parameters (Reynolds, Elsasser, etc.): par.TAG,
  - Additional diagnostics (heat fluxes, Nusselt numbers, etc.): misc.TAG.
- 3. There are **additional conditional time series** that contain the time-evolution of other physical quantities that depend on the chosen *input parameters*:
  - Angular momentum balance: AM.TAG,
  - Power budget: *power.TAG* and *dtE.TAG*,
  - Square velocities: u\_square.TAG,
  - Drift rates: drift[V\B][D\Q].TAG and iner[P\T].TAG,
  - Torques: SR[IC|MA].TAG,
  - RMS calculations of the force balances: dtVrms.TAG, dtBrms.TAG and dtDrms.TAG,
  - Kinetic energies perpendicular and parallel to the rotation axis: *perpPar.TAG*.
- 4. Time-averaged radial profiles:
  - Kinetic energies: eKinR.TAG,
  - Magnetic energies: *eMagR.TAG*,
  - Diagnostic quantities: parR.TAG,
  - Power budget: powerR.TAG,
  - Heat fluxes: fluxesR.TAG,

- Temperature and horizontal velocities: bLayersR.TAG,
- Kinetic energies perpendicular and parallel to the rotation axis: *perpParR.TAG*.
- 5. **Radial profiles of the transport properties** of the reference state (those files will only be produced when the appropriate input option is chosen):
  - Temperature, density and gravity: anel.TAG,
  - Electrical conductivity: varCond.TAG,
  - Thermal conductivity: varDiff.TAG,
  - Kinematic viscosity: varVisc.TAG,
  - Mapping of the Chebyshev grid: *rNM.TAG*.
- 6. Kinetic energy, magnetic energy and temperature/entropy spectra:
  - Kinetic energy: kin\_spec\_#.TAG,
  - Magnetic energy: kin\_spec\_#.TAG,
  - Velocity square: u2\_spec\_#.TAG,
  - Temperature/entropy: T\_spec\_#.TAG,
  - Time-averaged kinetic energy: kin\_spec\_ave.TAG,
  - Time-averaged magnetic energy: mag\_spec\_ave.TAG,
  - Time-averaged temperature/entropy: *T\_spec\_ave.TAG*,
  - 2-D ([r,ell] and [r,m]) spectra: 2D\_[mag|kin|u2]\_spec\_#.TAG.
- 7. Output snapshot that contains the 3-D components of the velocity field, the magnetic field and the temperature/entropy. Those files are named **graphic files** *G\_#.TAG* (or *G\_ave.TAG* for its time-averaged counterpart).
- 8. Time evolution of some chosen fields. Those files are named **movie files**: \* mov.TAG.
- 9. Checkpoints outputs that will allow the code to restart. Those files are named **restart files**: rst\_end.TAG.
- 10. **Time-evolution of the poloidal and toroidal coefficients** at diffent depths:
  - Time evolution of the poloidal magnetic field at the CMB: B\_coeff\_cmb.TAG,
  - Time evolution of the potentials at several depths: [V|T|B]\_coeff\_r#.TAG
- 11. Additional specific outputs:
  - Torsional oscillations (see *here*),
  - Potential files: Vpot #.TAG, Bpot #.TAG and Tpot #.TAG,
  - Potential vorticity files: PVZ.TAG and Vcy.TAG,
  - Magnetic spectra for various radii: rB[r|p]Spec.TAG.

# 8.1 Log file: log. TAG

This is a text file contains information about the run, including many of the things which are printed to STDOUT. It has the following information in order of appearance:

- Code version: the version of the code
- **Parallelization**: information about number of MPI ranks being used, blocking information of OpenMP chunks and processor load balancing

- Namelists: displays values of all namelist variables. The ones input by the user should have the input values while the rest of them are set to their default values.
- Mode The mode of the run self-consistent/kinematic dynamo, convection, couette flow etc. See the control
  namelist for more information about mode.
- **Grid parameters**: information about the grid sizes and truncation being used. More information about this in the *grid namelist*. If a new grid, different from that in the restart file is used, then a comparison is shown between old and new grid parameters and the user is informed that the data is being mapped from the old to the new grid.
- **Progress**: information about the progress of the run for every 10% of the run and the mean wall time for time step.
- Writing of graphic, movie, restart and spectra files: displays the time step and tells the user whenever a  $G_{\#}.TAG$ ,  $rst_{\#}.TAG$  or spectra file or a movie frame is written disk.
- Energies: gives kinetic and magnetic energies (total, poloidal, toroidal, total density) at the end of the run.
- **Time averages**: this part gives time averaged kinetic and magnetic energies (total, poloidal, toroidal, total density) and time averaged parameters (Rm, Elsass, Rol etc.). If *l\_average=.true*., this section also provides information about average spectra and graphic files being written.
- Wall times: this is the last part of the log file and it provides information about the mean wall time for running different parts of the code. These values can be used to judge the speed and scaling capabilities of your computer.

Most of these informations can be parsed and stored into a python class using MagicSetup:

```
>>> # read log.N0m2
>>> stp = MagicSetup(nml='log.N0m2')
>>> print(stp.ek, stp.prmag) # print Ekman and magnetic Prandtl numbers
>>> print(stp.l_max) # print l_max
```

# 8.2 Default time-series outputs

#### 8.2.1 e kin. TAG

This file contains the kinetic energy of the outer core, defined by

$$E_{k} = \frac{1}{2} \int_{V} \tilde{\rho} u^{2} \, dV = E_{pol} + E_{tor}$$

$$= \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \frac{1}{\tilde{\rho}} \left[ \frac{\ell(\ell+1)}{r^{2}} |W_{\ell m}|^{2} + \left| \frac{dW_{\ell m}}{dr} \right|^{2} \right] dr$$

$$+ \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \frac{1}{\tilde{\rho}} |Z_{\ell m}|^{2} dr$$
(8.1)

The detailed calculations are done in the subroutine  $get_ekin$ . This file contains the following informations:

No. of column	Contents
1	time
2	poloidal energy
3	toroidal energy
4	axisymmetric poloidal energy
5	axisymmetric toroidal energy
6	equatorial symmetric poloidal energy
7	equatorial symmetric toroidal energy
8	equatorial symmetric and axisymmetric poloidal energy
9	equatorial symmetric and axisymmetric toroidal energy

This file can be read using MagicTs with the following options:

```
>>> # To stack all the e_kin.TAG files of the current directory
>>> ts = MagicTs(field='e_kin', all=True)
>>> # To only read e_kin.NOm2
>>> ts = MagicTs(field='e_kin', tag='NOm2')
```

## 8.2.2 e\_mag\_oc.TAG

This file contains the magnetic energy of the outer core, defined by

$$E_{m} = \frac{1}{2} \int_{V} B^{2} dV = E_{pol} + E_{tor}$$

$$= \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \left[ \frac{\ell(\ell+1)}{r^{2}} |b_{\ell m}|^{2} + \left| \frac{db_{\ell m}}{dr} \right|^{2} \right] dr$$

$$+ \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} |j_{\ell m}|^{2} dr$$
(8.2)

The detailed calculations are done in the subroutine get\_e\_mag. This file contains the following informations:

No. of column	Contents
1	time
2	outer core poloidal energy
3	outer core toroidal energy
4	outer core axisymmetric poloidal energy
5	outer core axisymmetric toroidal energy
6	outside potential field energy
7	outside axisymmetric potential field energy
8	equatorial symmetric poloidal energy
9	equatorial symmetric toroidal energy
10	equatorial symmetric and axisymmetric poloidal energy
11	equatorial symmetric and axisymmetric toroidal energy
12	outside potential field energy
13	outside potential field axisymmetric energy

This file can be read using MagicTs with the following options:

```
>>> # To stack all the e_mag_oc.TAG files of the current directory
>>> ts = MagicTs(field='e_mag_oc', all=True)
>>> # To only read e_mag_oc.N0m2
>>> ts = MagicTs(field='e_mag_oc', tag='N0m2')
```

## 8.2.3 e\_mag\_ic.TAG

This file contains the magnetic energy of the inner core. The detailed calculations are done in the subroutine  $get\_e\_mag$ . This file contains the following informations:

No. of column	Contents
1	time
2	inner core poloidal energy
3	inner core toroidal energy
4	inner core axisymmetric poloidal energy
5	inner core axisymmetric toroidal energy

This file can be read using MagicTs with the following options:

```
>>> # To stack all the e_mag_ic.TAG files of the current directory
>>> ts = MagicTs(field='e_mag_ic', all=True)
>>> # To only read e_mag_ic.NOm2
>>> ts = MagicTs(field='e_mag_ic', tag='N0m2')
```

#### 8.2.4 rot. TAG

This files contains the rotation of the inner core and the mantle. Output concerning the rotation of inner core and mantle. This file is written by the subroutine write\_rot.

No. of column	Contents
1	time
2	Inner core rotation rate
3	Lorentz torque on inner core
4	viscous torque on inner core
5	mantle rotation rate
6	Lorentz torque on mantle
7	viscous torque on mantle

This file can be read using MagicTs with the following options:

```
>>> # To stack all the rot.TAG files of the current directory
>>> ts = MagicTs(field='rot', iplot=False, all=True)
```

## 8.2.5 dipole. TAG

This file contains several informations about the magnetic dipole. This file is written by the subroutine get\_e\_mag.

No. of	Contents
column	
1	time
2	tilt angle (colatitude in degrees) of the dipole
3	longitude (in degress) of dipole-pole
4	relative energy of the axisymmetric dipole
5	relative energy of the axisymmetric dipole at the CMB
6	energy of the axisymmetric dipole at the CMB normalized with the total energy up to
	spherical harmonic degree and order 11
7	relative energy of the total (axisymmetric and equatorial) dipole
8	relative energy of the total (axisymmetric and equatorial) dipole in the outer core
9	relative energy of the total dipole (axisymmetric and equatorial) at the CMB
10	energy of the total (axisymmetric and equatorial) dipole at the CMB
11	energy of the axisymmetric dipole at the CMB
12	energy of the dipole
13	energy of the axisymmetric dipole
14	magnetic energy at the CMB
15	magnetic energy up to spherical harmonic degree and order 11
16	ratio between equatorial dipole energy and equatorial poloidal energy
17	difference between energy at the CMB and equatorial symmetric energy at the CMB,
	normalized by energy at the CMB
18	difference between energy at the CMB and axisymmetric energy at the CMB,
	normalized by energy at the CMB
19	difference between total energy and equatorial symmetric part of the total energy,
	normalized by the total energy
20	difference between total energy and axisymmetric part of the total energy, normalized
	by the total energy

This file can be read using MagicTs with the following options:

```
>>> # To stack all the dipole.TAG files of the current directory
>>> ts = MagicTs(field='dipole', all=True)
```

## 8.2.6 par. TAG

This files contains the outputs of several parameters that describe flow and magnetic fields (Reynolds number, Elsasser number, flow lengthscales, etc.). This file is written by the subroutine output.

No. of column	Contents
1	time
2	(magnetic) Reynolds number
3	Elsasser number
4	Local Rossby number Rol
5	Realtive geostrophic kinetic energy
6	Total dipolarity
7	CMB dipolarity
8	Axial flow length scale dlV
9	Flow length scale dmV
10	Flow length scale dpV
11	Flow length scale dzV
12	Dissipation length scale lvDiss
13	Dissipation length scale lbDiss
14	Magnetic length scale dlB
15	Magnetic length scale dlB
16	Elsasser number at CMB
17	Local Rol based on non-ax. flow
18	Convective flow length scale dlVc
19	CMB zonal flow at the equator

This file can be read using MagicTs with the following options:

```
>>> # To stack all the par.TAG files of the current directory
>>> ts = MagicTs(field='par', all=True)
```

#### 8.2.7 misc. TAG

This files contains informations about heat transfer (Nusselt number and temperature at both boundaries), as well as various additional informations (helicity, geostrophy, etc.). This file is written by the subroutine <code>outMisc</code>.

**Note:** The columns 6-9 and 17-20 are **only** calculated when  $l\_hel=.true$ .. The columns 10-16 are only calculated when  $l\_par=.true$ ..

No. of column	Contents
1	time
2	Nusselt number at the inner core
3	CMB Nusselt number at the CMB
4	Entropy at the inner core
5	Entropy at the CMB
6	Helicity (northern hemisphere)
7	Helicity (southern hemisphere)
8	RMS helicity (northern hemisphere)
9	RMS helicity (southern hemisphere)
10	Relative geostrophic kinetic energy
11	Relative kinetic energy in the northern part of the TC
12	Relative kinetic energy in the southern part of the TC
13	Kinetic energy
14	North/South correlation of Vz, outside the TC
15	North/South correlation of vorticity outside the TC
16	North/South correlation of helicity outside the TC

```
>>> # To stack all the misc.TAG files of the current directory
>>> ts = MagicTs(field='misc', all=True)
```

## 8.3 Additional optional time-series outputs

#### 8.3.1 AM. TAG

**Note:** This file is **only** written when  $l\_AM = .true$ .

This file contains the time series of the angular momentum of the inner core, the outer core and the mantle. This file is written by the subroutine write\_rot.

No. of column	Contents
1	time
2	angular momentum of the outer core
3	angular momentum of the inner core
4	angular momentum of the mantle
5	total angular momentum
6	relative in angular momentum, per time step
7	total kinetic angular momentum
8	relative change in kinetic energy, per time step
9	kinetic angular momentum of the inner core
10	kinetic angular momentum of the outer core
11	kinetic angular momentum of the mantle

This file can be read using MagicTs with the following options:

```
>>> # To stack all the AM.TAG files of the current directory
>>> ts = MagicTs(field='AM', all=True)
```

## 8.3.2 power.TAG

**Note:** This file is **only** written when  $l\_power=.true$ .

This file contains the power budget diagnostic. This file is computed by the subroutine get\_power.

No. of column	Contents
1	time
2	Buoyancy power: $Ra g(r) \langle u_r T' \rangle_s$
3	Viscous power at the inner boundary (ICB)
4	Viscous power at the outer boundary (CMB)
5	Viscous dissipation: $\langle (\nabla \times u)^2 \rangle_s$
6	Ohmic dissipation: $\langle (\nabla \times B)^2 \rangle_s$
7	Total power at the CMB (viscous + Lorentz)
8	Total power at the ICB (viscous + Lorentz)
9	Total power
10	Time variation of total power

```
>>> # To stack the files that match the pattern ``power.N0m2*``
>>> ts = MagicTs(field='power', tags='N0m2*')
```

#### 8.3.3 dtE.TAG

**Note:** This file is **only** written when  $l\_power=.true$ .

This file contains the time-derivatives of the total energy. It allows to accurately monitor how the total energy varies with time. This file is generated by the subroutine *output*.

No. of column	Contents
1	time
2	time-derivative of the total energy $\partial E/\partial t$
3	integrated time variation of the total energy
4	relative time variation of the total energy

## 8.3.4 u\_square.TAG

**Note:** This file is **only** written in an elastic models, i.e. either when *strat/=0* or when *interior\_model/="None"* 

This file contains the square velocity of the outer core. It is actually very similar to the  $e\_kin.TAG$  file, except that the density background  $\tilde{\rho}$  is removed:

$$\mathcal{U} = \frac{1}{2} \int_{V} u^{2} \, dV = \mathcal{U}_{pol} + \mathcal{U}_{tor}$$

$$= \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \frac{1}{\tilde{\rho}^{2}} \left[ \frac{\ell(\ell+1)}{r^{2}} |W_{\ell m}|^{2} + \left| \frac{dW_{\ell m}}{dr} \right|^{2} \right] dr$$

$$+ \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \frac{1}{\tilde{\rho}^{2}} |Z_{\ell m}|^{2} dr$$

The detailed calculations are done in the subroutine  $get\_u\_square$ . This file contains the following informations:

No. of columns	Contents
1	time
2	poloidal part $\mathcal{U}_{pol}$
3	toroidal part $\mathcal{U}_{pol}$
4	axisymmetric contribution to the poloidal part
5	axisymmetric contribution to the toroidal part
6	Rossby number: $Ro = E\sqrt{\frac{2U}{V}}$
7	Magnetic Reynolds number: $Rm = Pm \sqrt{\frac{2\mathcal{U}}{V}}$
8	local Rossby number: $Ro_l = Ro \frac{d}{l}$
9	average flow length scale: l
10	local Rossby number based on the non-axisymmetric components of the flow
11	average flow length scale based on the non-axisymmetric components of the flow

```
>>> # To stack all the u_square.TAG files of the current directory
>>> ts = MagicTs(field='u_square', all=True)
```

## 8.3.5 drift[V|B][D|Q].TAG

**Note:** These files are **only** written when  $l\_drift = .true$ .

These files store spherical harmonic coefficients of the toroidal (poloidal) potential of the flow (magnetic) field, only for  $\ell=m$  or  $\ell=m+1$  depending on the symmetry - D for  ${\bf D}$  ipolar and Q for  ${\bf Q}$  uadrupolar. The coefficients are stored at different three different radial levels - n\_r1, nr\_2, n\_r3 for the velocity and two different radial levels - n\_r1 and n\_r2 - for the magnetic field.

The symmetries can be summarized below:

Field	Dipolar	Quadrupolar
Velocity	$\ell = m$	$\ell = m + 1$
Magnetic	$\ell = m + 1$	$\ell = m$

 $\ell+m=$  even for toroidal potential refers to an equatorially antisymmetric field (Dipolar), while the same for a poloidal potential is associated with an equatorially symmetric field (Quadrupolar). The sense is opposite when  $\ell+m=$  odd. This is the reason for the choice of selecting these specific coefficients.

The columns of the files look like follows:

For the flow field:

- $n_r1 = (1/3) * n_r_max-1$
- $n_r2 = (2/3) * n_r_max-1$
- $n_r3 = n_r_{max-1}$

Column no.	DriftVD.TAG	DriftVQ.TAG
1	Time	Time
2	z (minc, minc) at n_r1	$z (minc+1, minc)$ at n_r1
3	z (2*minc, 2*minc) at n_r1	z (2*minc+1, 2*minc) at n_r1
4	z (3*minc, 3*minc) at n_r1	z (3*minc+1, 3*minc) at n_r1
5	z (4*minc, 4*minc) at n_r1	z (4*minc+1, 4*minc) at n_r1
6	z (minc, minc) at n_r2	z (minc+1, minc) at n_r2
7	z (2*minc, 2*minc) at n_r2	z (2*minc+1, 2*minc) at n_r2
8	z (3*minc, 3*minc) at n_r2	z (3*minc+1, 3*minc) at n_r2
9	z (4*minc, 4*minc) at n_r2	z (4*minc+1, 4*minc) at n_r2
10	z (minc, minc) at n_r3	z (minc+1, minc) at n_r3
11	z (2*minc, 2*minc) at n_r3	z (2*minc+1, 2*minc) at n_r3
12	z (3*minc, 3*minc) at n_r3	z (3*minc+1, 3*minc) at n_r3
13	z (4*minc, 4*minc) at n_r3	z (4*minc+1, 4*minc) at n_r3

For the magnetic field:

- $n_r1 = n_rICB$
- $n_r2 = n_r CMB$

Column no.	DriftBD.TAG	DriftBQ.TAG
1	Time	Time
2	b (minc+1, minc) at n_r1	b (minc, minc) at n_r1
3	b (2*minc+1, 2*minc) at n_r1	b (2*minc, 2*minc) at n_r1
4	b (3*minc+1, 3*minc) at n_r1	<i>b</i> (3*minc, 3*minc) at n_r1
5	b (4*minc+1, 4*minc) at n_r1	b (4*minc, 4*minc) at n_r1
6	b (minc+1, minc) at n_r2	b (minc, minc) at n_r2
7	b (2*minc+1, 2*minc) at n_r2	b (2*minc, 2*minc) at n_r2
8	b (3*minc+1, 3*minc) at n_r2	<i>b</i> (3*minc, 3*minc) at n_r2
9	b (4*minc+1, 4*minc) at n_r2	b (4*minc, 4*minc) at n_r2

Analysis of these files can give you information about the drift frequency of the solution and it's symmetry.

#### 8.3.6 iner[P|T].TAG

**Note:** These files are **only** written when  $l\_iner=.true$ . and minc = 1.

These files contain time series of spherical harmonic coefficients upto degree,  $\ell=6$  at a radius  $r=(r_{cmb}-r_{icb})/2$ . The inerp.TAG contains coefficients of the poloidal potential while the inerp.TAG contains coefficients of the toroidal potential. These files are written by the subroutine  $write\_rot$ . The oscillations of these coefficients can be analysed to look for inertial modes. The columns of the inerp.TAG look like follows:

No. of column	Coefficient
1	$w(\ell=1, m=1)$
2	$w(\ell=2, m=1)$
3	$w(\ell=2, m=2)$
4	$w(\ell=3, m=1)$
20	$w(\ell = 6, m = 5)$
21	$w(\ell = 6, m = 6)$

where  $w(\ell, m)$  is the poloidal potential with degree  $\ell$  and order m.

The columns of the inerT.TAG follow the following structure:

No. of column	Coefficient
1	$z(\ell=1, m=1)$
2	$z(\ell=2, m=1)$
3	$z(\ell=2, m=2)$
4	$z(\ell=3, m=1)$
20	$z(\ell=6, m=5)$
21	$z(\ell=6, m=6)$

where  $z(\ell, m)$  is the toroidal potential with degree  $\ell$  and order m.

#### 8.3.7 SR[IC|MA].TAG

**Note:** These files are **only** written for nRotIc=-1 (for SRIC.TAG) or nRotMa=-1 (for SRMA.TAG). In other words, these outputs are produced **only** when one of the boundaries is made to rotate at a prescribed rotation rate.

These files contain information about power due to torque from viscous and Lorentz forces at the inner core boundary (SRIC.TAG) or core mantle boundary (SRMA.TAG). The columns look like follows:

No. of column	Contents
1	Time
2	$\Omega_{IC} \Omega_{MA}$
3	Total power = Lorentz + Viscous
4	Viscous power
5	Lorentz force power

#### 8.3.8 dtVrms.TAG

**Warning:** The RMS calculation is actually wrong in the current version. This needs again to be ported from MagIC 3.44. This issue only affects dtVrms.TAG, though. A ticket has been opened on github regarding this issue: https://github.com/magic-sph/magic/issues/1

**Note:** This file is **only** written when  $l\_RMS=.true$ .

This files contains the RMS force balance of the Navier Stokes equation. This file is written by the subroutine dt Vrms.

No. of column	Contents
1	time
2	Poloidal flow changes: inertia-advection
3	Toroidal flow changes: inertia-advection
4	Poloidal Coriolis force
5	Toroidal Coriolis force
6	Poloidal Lorentz force
7	Toroidal Lorentz force
8	Poloidal advection term
9	Toroidal advection term
10	Poloidal diffusion term
11	Toroidal diffusion term
12	Buoyancy term
13	Pressure gradient term
14	Sum of force terms: geostrophic balance
15	Sum of force terms: magnetostrophic balance
16	Sum of force terms: Archemidian balance

This file can be read using MagicTs with the following options:

```
>>> # To stack all the dtVrms.TAG files of the current directory
>>> ts = MagicTs(field='dtVrms', all=True)
```

#### 8.3.9 dtBrms.TAG

**Note:** This file is **only** written when  $l\_RMS=.true$ .

This files contains the RMS terms that enter the induction equation. This file is written by the subroutine dtBrms.

No. of column	Contents
1	time
2	Changes in magnetic field (poloidal)
3	Changes in magnetic field (toroidal)
4	Poloidal strecthing term
5	Toroidal strecthing term
6	Poloidal field advection term
7	Toroidal field advection term
8	Poloidal diffusion term
9	Toroidal diffusion term
10	Omega effect / toroidal strecthing term
11	Omega effect
12	Poloidal field production (stretching+advection)
13	Toroidal field production (stretching+advection)

This file can be read using *MagicTs* with the following options:

```
>>> # To stack all the dtBrms.TAG files of the current directory
>>> ts = MagicTs(field='dtBrms', all=True)
```

#### 8.3.10 dtDrms.TAG

**Note:** This file is **only** written when  $l\_RMS=.true$ .

This files contains the RMS terms that enter the induction equation of the dipole. This file is written by the subroutine dtBrms.

No. of column	Contents
1	time
2	Dipole stretching
3	Dipole advection term
4	Dipole diffusion term

### 8.3.11 perpPar.TAG

**Note:** This file is **only** written when  $l\_perpPar=.true$ .

This file contains several time series that decompose the kinetic energy into components parallel and perpendicular to the rotation axis. This file is calculated by the subroutine <code>outPerpPar</code>.

No. of column	Contents
1	radial level
2	Total kinetic energy perpendicular to the rotation axis: $\frac{1}{2}\langle u_s^2 + u_\phi^2 \rangle_V$
3	Total kinetic energy parallel to the rotation axis: $\frac{1}{2}\langle u_z^2\rangle_V$
4	Axisymmetric kinetic energy perpendicular to the rotation axis
5	Axisymmetric kinetic energy parallel to the rotation axis

```
>>> # To stack all the perpPar.TAG files of the current directory
>>> ts = MagicTs(field='perpPar', all=True)
```

# 8.4 Time-averaged radial profiles

#### 8.4.1 eKinR.TAG

This file contains the time and horizontally averaged outer core kinetic energy along the radius. This file is calculated by the subroutine  $get_e_kin$ .

No. of	Contents
column	
1	radial level
2	time and horizontally averaged poloidal energy
3	time and horizontally averaged axisymmetric poloidal energy
4	time and horizontally averaged toroidal energy
5	time and horizontally averaged axisymmetric toroidal energy
6	time and horizontally averaged poloidal energy, normalized by surface area at this
	radial level
7	time and horizontally averaged axisymmetric poloidal energy, normalized by surface
	area at this radial level
8	time and horizontally averaged toroidal energy, normalized by surface area at this
	radial level
9	time and horizontally averaged axisymmetric toroidal energy, normalized by surface
	area at this radial level

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='eKinR')
```

## 8.4.2 eMagR.TAG

This file contains the time and horizontally averaged outer core magnetic energy along the radius. This file is calculated by the subroutine  $get\_e\_mag$ .

No. of	Contents
column	
1	radial level
2	time and horizontally averaged poloidal energy
3	time and horizontally averaged axisymmetric poloidal energy
4	time and horizontally averaged toroidal energy
5	time and horizontally averaged axisymmetric toroidal energy
6	time and horizontally averaged poloidal energy, normalized by surface area at this
	radial level
7	time and horizontally averaged axisymmetric poloidal energy, normalized by surface
	area at this radial level
8	time and horizontally averaged toroidal energy, normalized by surface area at this
	radial level
9	time and horizontally averaged axisymmetric toroidal energy, normalized by surface
	area at this radial level
10	ratio between time-averaged dipole energy and time-averaged total energy

```
>>> rad = MagicRadial(field='eMagR')
```

## 8.4.3 parR.TAG

This file contains several time and horizontally averaged flow properties (magnetic Reynolds number, Rossby number, etc.). This file is calculated by the subroutine outPar.

No. of	Contents
column	
1	radial level
2	Magnetic Reynolds number
3	Local Rossby number (based on the mass-weighted velocity)
4	Local Rossby number (based on the RMS velocity)
5	Local flow length-scale (based on the mass-weighted velocity)
6	Local flow length-scale based on the non-axisymmetric flow components (based on
	the mass-weighted velocity)
7	Local flow length-scale (based on the RMS velocity)
8	Local flow length-scale based on the non-axisymmetric flow components (based on
	the RMS velocity)

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='parR')
```

## 8.4.4 powerR.TAG

**Note:** This file is **only** written when  $l\_power=.true$ .

This file contains the time and horizontally averaged power input (Buoyancy power) and outputs (viscous and Ohmic heating). This file is calculated by the subroutine  $get\_power$ .

No. of column	Contents
1	radial level
2	Buoyancy power: $Rag(r) \langle u_r T' \rangle_s$
3	Viscous dissipation: $\langle (\nabla \times u)^2 \rangle_s$
4	Ohmic dissipation: $\langle (\nabla \times B)^2 \rangle_s$

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='powerR')
```

#### 8.4.5 fluxesR.TAG

**Note:** This file is **only** written when  $l_fluxProfs=.true$ .

This file contains the time and horizontally averaged heat flux carried out by several physical processes: conductive flux, convective flux, kinetic flux, viscous flux, Poynting flux and resistive flux. This file is calculated by the subroutine outPar.

No. of column	Contents
1	radial level
2	conductive flux:
	$\mathcal{F}_{cond} = -rac{1}{Pr}\kappa ilde{ ho} ilde{T}rac{\partial\langle s angle_s}{\partial r}$
3	convective flux:
	$\mathcal{F}_{conv} = \tilde{\rho}\tilde{T}\langle s  u_r \rangle_s + \frac{Pr  Di}{E  Ra} \langle p  u_r \rangle_s$
4	kinetic flux:
	$\mathcal{F}_{kin} = \frac{1}{2} \frac{Pr  Di}{Ra} \langle u_r(\tilde{\rho}u^2) \rangle_s$
5	viscous flux:
	$\mathcal{F}_{visc} = -rac{PrDi}{Ra}\langle m{u}\cdot S angle_s$
6	Poynting flux:
	${\cal F}_{poyn} = -rac{PrDi}{RaEPm} \langle (m{u} imesm{B}) imesm{B} angle_s$
7	resistive flux:
	$\mathcal{F}_{poyn} = rac{PrDi}{RaEPm^2} \langle (oldsymbol{ abla}  imes oldsymbol{B})  imes oldsymbol{B}  angle_s$

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='fluxesR')
```

## 8.4.6 bLayersR.TAG

**Note:** This file is **only** written when  $l\_viscBcCalc=.true$ .

This file contains several time and horizontally averaged profiles that can be further used to determine thermal and viscous boundary layers: entropy (or temperature), entropy variance, horizontal velocity, radial derivative of the horizontal velocity, thermal dissipation rate. This file is calculated by the subroutine <code>outPar</code>.

No. of column	Contents
1	radial level
2	entropy: $\langle s \rangle_s$
3	entropy variance:
	$\sqrt{\langle (s - \langle s \rangle_s)^2 \rangle_s}$
4	horizontal velocity:
	$u_h = \left\langle \sqrt{u_\theta^2 + u_\phi^2} \right\rangle_s$
5	radial derivative of the horizontal velocity:
	$\partial u_h/\partial r$
6	thermal dissipation rate:
	$\epsilon_T = \langle (\nabla T)^2 \rangle_s$

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='bLayersR')
```

Additional analyses of the boundary layers can then be carried out using BLayers:

```
>>> bl = BLayers(iplot=True)
```

## 8.4.7 perpParR.TAG

**Note:** This file is **only** written when  $l\_perpPar=.true$ .

This file contains several time and horizontally averaged profiles that decompose the kinetic energy into components parallel and perpendicular to the rotation axis. This file is calculated by the subroutine <code>outPerpPar</code>.

No. of column	Contents
1	radial level
2	Total kinetic energy perpendicular to the rotation axis:
	$\frac{1}{2}\langle u_s^2 + u_\phi^2 \rangle_s$
3	Total kinetic energy parallel to the rotation axis:
	$rac{1}{2}\langle u_z^2 angle_s$
4	Axisymmetric kinetic energy perpendicular to the rotation axis
5	Axisymmetric kinetic energy parallel to the rotation axis

```
>>> rad = MagicRadial(field='perpParR')
```

## 8.5 Transport properties of the reference state

These files define the radial transport properties of the reference state. These arrays are calculated in the subroutines radial and transportProperties. The output files are written in the subroutine preCalc.

#### 8.5.1 anel. TAG

**Note:** This output is only calculated when an anelastic model is run, that is when  $l\_anel=.true$ . or  $l\_anelastic\_liquid=.true$ .

This file contains the radial profiles of the reference state (density, temperature, gravity, etc.).

No. of column	Contents
1	radial level: r
2	temperature: $\tilde{T}(r)$
3	density: $\tilde{\rho}(r)$
4	radial derivative of the density: $\beta = d \ln \tilde{\rho}/dr$
5	radial derivative of $\beta$ : $d\beta/dr$
6	gravity: $g(r)$
7	entropy gradient: $ds_0/dr$
8	thermal diffusion operator: $\nabla \cdot (K(r)\tilde{T}(r)\nabla s_0)$

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='anel')
>>> # print radius and density
>>> print(rad.radius, rad.rho0)
```

#### 8.5.2 varCond. TAG

**Note:** This output is only calculated when the electrical conductivity varies with radius, i.e. when  $nVarCond \neq 0$ 

This file contains the radial profiles of the electrical conductivity, the electrical diffusivity and its radial derivative.

No. of column	Contents	
1	radial level: r	
2	electrical conductivity: $\sigma(r)$	
3	electrical diffusivity: $\lambda(r) = 1/\sigma(r)$	
4	radial derivative of the electrical diffusivity: $d \ln \lambda / dr$	

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='varCond')
>>> print(rad.conduc) # Electrical conductivity
```

### 8.5.3 varDiff.TAG

**Note:** This output is only calculated when the thermal diffusivity varies with radius, i.e. when nVarDiff = 0

This file contains the radial profiles of the thermal conductivity, the thermal diffusivity and its radial derivative.

No. of column	Contents	
1	radial level: r	
2	thermal conductivity: $K(r)$	
3	thermal diffusivity: $\kappa(r) = K(r)/\tilde{\rho}(r)$	
4	radial derivative of the electrical diffusivity: $d \ln \kappa / dr$	
5	Prandtl number: $Pr(r) = \nu(r)/\kappa(r)$	

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='varDiff')
>>> print(rad.kappa) # Thermal diffusivity
```

#### 8.5.4 varVisc.TAG

**Note:** This output is only calculated when the kinematic viscosity varies with radius, i.e. when  $nVarVisc \neq 0$ 

This file contains the radial profiles of the dynamic viscosity, the kinematic viscosity and its radial derivative.

No. of column	Contents	
1	radial level: r	
2	dynamic viscosity: $\mu(r)$	
3	kinetmatic viscosity: $\nu(r) = \mu(r)/\tilde{\rho}(r)$	
4	radial derivative of the kinematic viscosity: $d \ln \nu / dr$	
5	Prandtl number: $Pr(r) = \nu(r)/\kappa(r)$	
6	magnetic Prandtl number $Pm(r) = \nu(r)/\lambda(r)$	

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='varVisc')
>>> # print kinematic viscosity and Ekman
>>> print(rad.kinVisc, rad.ekman)
```

## 8.6 Nonlinear mapping of the Chebyshev grid

#### 8.6.1 rNM. TAG

**Note:** This file is only written when  $l_newmap = .true$ ..

This file contains the profile of the radial mapping and its derivatives:

No. of column	Contents	
1	Grid point index	
2	Radius of a grid point	
3	First derivative of the mapping at a grid point	
4	Second derivative of the mapping at a grid point	
5	Third derivative of the mapping at a grid point	

## 8.7 Spectra

#### 8.7.1 kin\_spec\_#.TAG

This file contains the kinetic energy spectra. This file is written by the subroutine spectrum.

No. of column	Contents
1	degree / order
2	Poloidal kinetic energy versus degree
3	Poloidal kinetic energy versus order
4	Toroidal kinetic energy versus degree
5	Toroidal kinetic energy versus order

This file can be read using MagicSpectrum with the following options:

```
>>> sp = MagicSpectrum(field='ekin')
```

## 8.7.2 mag\_spec\_#.TAG

This file contains the magnetic energy spectra. This file is written by the subroutine spectrum.

No. of column	Contents	
1	degree / order	
2	Poloidal magnetic energy in the outer core versus degree	
3	Poloidal magnetic energy in the outer core versus order	
4	Toroidal magnetic energy in the outer core versus degree	
5	Toroidal magnetic energy in the outer core versus order	
6	Poloidal magnetic energy in the inner core versus degree	
7	Poloidal magnetic energy in the inner core versus order	
8	Toroidal magnetic energy in the inner core versus degree	
9	Toroidal magnetic energy in the inner core versus order	
10	Poloidal magnetic energy at the CMB versus degree	
11	Poloidal magnetic energy at the CMB versus order	
12	Poloidal magnetic energy at the CMB	

This file can be read using MagicSpectrum with the following options:

```
>>> sp = MagicSpectrum(field='emag')
```

#### 8.7.3 u2\_spec\_#.TAG

**Note:** This file is **only** written in an elastic models, i.e. either when *strat/=0* or when *interior\_model/="None"* 

This file contains the spectra of the square velocity. This file is written by the subroutine spectrum.

No. of column	Contents	
1	degree / order	
2	Poloidal contribution per degree in the outer core	
3	Poloidal contribution per order in the outer core	
4	Toroidal contribution per degree in the outer core	
5	Toroidal contribution per order in the outer core	

```
>>> # To read the file ``u2_spec_1.test``:
>>> sp = MagicSpectrum(field='u2', ispec=1, tag='test')
```

## 8.7.4 T\_spec\_#.TAG

This file contains the temperature/entropy spectra. It is written by the subroutine <code>spectrum\_temp</code>.

No. of column	Contents	
1	degree / order	
2	RMS temperature/entropy versus degree	
3	RMS temperature/entropy versus order	
4	RMS temperature/entropy at the ICB versus degree	
5	RMS temperature/entropy at the ICB versus order	
6	RMS radial derivative of temperature/entropy at the ICB versus degree	
7	RMS radial derivative of temperature/entropy at the ICB versus order	

### 8.7.5 2D spectra [2D\_kin|mag|u2\_spec]\_#.TAG

Those files contain 2-D spectra in the  $(r,\ell)$  and in the (r,m) planes. In other words, the poloidal and toroidal energies versus degree  $\ell$  or versus order m are computed for all radii. There are three kinds of those files that correspond to the aforementioned spectra, namely  $2D_kin_spec_\#.TAG$ ,  $2D_mag_spec_\#.TAG$  and  $2D_u2_spec_\#.TAG$ . The calculations are done in the subroutine spectrum. The structure of the output files are same for these three outputs. They are stored as fortran unformatted files.

Unformatted files are not directly human readable, and are used to store binary data and move it around without changing the internal representation. In fortran, the open, read and write operations for these files are performed as follows:

```
open(unit=4, file='test', form='unformatted')
read(unit=4) readVar
write(unit=n_out, iostat=ios) writeVar !Unformatted write
```

The structure of the 2D spectra files are as follows:

8.7. Spectra 83

Those files can be read using the python class <code>MagicSpectrum2D</code> with the following options:

```
>>> # Read the file 2D_mag_spec_3.ext
>>> sp = MagicRSpec(tag='ext', field=e_mag', ispec=3)
>>> # Print e_pol_1 and e_tor_m
>>> print(sp.e_pol_1, sp.e_tor_m)
```

#### 8.7.6 kin\_spec\_ave.TAG

**Note:** This file is **only** written when  $l\_average=.true$ .

This file contains the time-average kinetic energy spectra as well as squared quantities to allow a possible further reconstruction of the standard deviation. This file is written by the subroutine <code>spectrum\_average</code>.

No. of column	Contents	
1	degree / order	
2	Time-averaged poloidal kinetic energy versus degree	
3	Time-averaged poloidal kinetic energy versus order	
4	Time-averaged toroidal kinetic energy versus degree	
5	Time-averaged toroidal kinetic energy versus order	
6	Time-averaged poloidal kinetic energy square versus degree	
7	Time-averaged poloidal kinetic energy square versus order	
8	Time-averaged toroidal kinetic energy square versus degree	
9	Time-averaged toroidal kinetic energy square versus order	

```
>>> # To read the file ``kin_spec_ave.test``:
>>> sp = MagicSpectrum(field='kin', ave=True, tag='test')
```

## 8.7.7 mag\_spec\_ave.TAG

**Note:** This file is **only** written when  $l\_average = .true$ . and the run is magnetic

This file contains the time-average magnetic energy spectra. This file is written by the subroutine <code>spectrum\_average</code>.

No. of	Contents	
column		
1	degree / order	
2	Time-averaged poloidal magnetic energy in the outer core versus degree	
3	Time-averaged poloidal magnetic energy in the outer core versus order	
4	Time-averaged toroidal magnetic energy in the outer core versus degree	
5	Time-averaged toroidal magnetic energy in the outer core versus order	
6	Time-averaged poloidal magnetic energy at the CMB versus degree	
7	Time-averaged poloidal magnetic energy at the CMB versus order	
8	Time-averaged poloidal magnetic energy in the outer core + its standard deviation versus degree	
9	Time-averaged poloidal magnetic energy in the outer core - its standard deviation versus degree	
10	Time-averaged poloidal magnetic energy in the outer core + its standard deviation versus order	
11	Time-averaged poloidal magnetic energy in the outer core - its standard deviation versus order	
12	Time-averaged toroidal magnetic energy in the outer core + its standard deviation versus degree	
13	Time-averaged toroidal magnetic energy in the outer core - its standard deviation versus degree	
14	Time-averaged toroidal magnetic energy in the outer core + its standard deviation versus order	
15	Time-averaged toroidal magnetic energy in the outer core - its standard deviation versus order	
16	Time-averaged poloidal magnetic energy at the CMB + its standard deviation versus order	
17	Time-averaged poloidal magnetic energy at the CMB - its standard deviation versus order	

This file can be read using MagicSpectrum with the following options:

```
>>> # To read the file ``mag_spec_ave.test``:
>>> sp = MagicSpectrum(field='mag', ave=True, tag='test')
```

#### 8.7.8 T\_spec\_ave.TAG

**Note:** This file is **only** written when  $l\_average = .true$ .

This file contains the time-averaged temperature/entropy spectra and their standard deviation. It is written by the subroutine <code>spectrum\_temp\_average</code>.

8.7. Spectra 85

No. of column	Contents	
1	Spherical harmonic degree	
2	Time-averaged RMS temperature/entropy versus degree	
3	Standard deviation of the temperature/entropy versus degree	
4	Time-averaged RMS temperature/entropy at the ICB versus degree	
5	Standard deviation of the temperature/entropy at the ICB versus degree	
6	Time-averaged temperature/entropy gradient at the ICB versus degree	
7	Standard deviation of the temperature/entropy gradient at the ICB versus degree	

## 8.8 Graphic files G\_#.TAG and G\_ave.TAG

These are fortran unformatted files containing 3D data (in the form vector\_array(phi, theta, r)) which can be used to visualize the solution. They are written after a fixed number of time steps as specified by the user in the *Output Control namelist* using the parameters listed in the section on *output of graphic files*. In case  $l\_average$  is set to .true., then an average graphic file, named  $G\_ave.TAG$ , containing time averaged values of 3D data, is also written at the end of the simulation.

These files are written in chunks of latitude for one radial level at a time by the subroutine <code>graphOut</code> or by <code>graphOut\_mpi</code> depending on whether <code>USE\_MPI</code> is set to <code>Yes</code> or <code>No</code> in the Makefile. The structure of the file looks like below:

```
!----
! Line 1
version
                    !Graphout_version_9 (using MPI) or
                    !Graphout_version_7 (without MPI)
!----
! Line 2
1_____
runid
1_____
! Line 3
time, n_r_max, n_theta_max, n_phi_tot,
                                          !time = Time of writing
n_r_ic_max-1, minc, nThetasBs,
                                           ! (Simulation time),
ra, ek, pr, prmag,
                                           !nThetasBs = no. of
                                            !theta blocks
radratio, sigma_ratio
! Line 4
theta(1:n_theta_max)
!-----
!Graphout_version_9
! This version is written when the code uses MPI (USE_MPI=yes). Parallel
! chunks of fields are written for different radial levels. Chunks in theta
```

```
! are written in parallel using OpenMP
! Data
!----
! Block N
1_____
! Line 4 + N
!-----
n_r-1, r(n_r)/r(1), n_theta_start, n_theta_stop !Radial index, radius in terms
                                              !of r_cmb, start and stop of
                                              !the theta block
!----
! Line 4 + (N+1)
1_____
sr(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Entropy
! Line 4 + (N+2)
vr(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Radial velocity
! Line 4 + (N+3)
vt(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Theta component of velocity
1_____
! Line 4 + (N+4)
vp(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Zonal (phi component) of
                                              !velocity
if (l_mag):
                                               !For a magnetic run
  ! Line 4 + (N+5)
  1-----
 br(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Radial magnetic field
  ! Line 4 + (N+6)
  !----
 bt(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Theta component of
                                                !magnetic field
```

```
! Line 4 + (N+7)
  1_____
 bp(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Zonal (phi component)
                                         !of magnetic field
1_____
! {\it Graphout\_version\_7}
!-----
!This version is written when the code does not use MPI (USE_MPI=no).
!Chunks in theta are written in parallel with OpenMP.
! Data
1-----
!----
! Block N
1_____
! Line 4 + (N+1)
1_____
n_r-1, r(n_r)/r(1), n_t+1
! Each of the following data point is written in a new line
! Entropy
1-----
sr(2,n_theta_start,n_r)
                          !n_phi = 2, n_theta = n_theta_start, n_r
!n_phi = 1, n_theta = n_theta_start+1, n_r
sr(1,n_theta_start+1,n_r)
sr(n_phi_tot,n_theta_start+1,n_r)
                          !n_phi = 1, n_theta = n_theta_stop, n_r
sr(1, n_theta_stop, n_r)
sr(2,n_theta_stop,n_r)
                          !n_phi = 2, n_theta = n_theta_stop, n_r
sr(n_phi_tot,n_theta_stop,n_r)
                          !n_phi = n_phi_tot, n_theta = n_theta_stop, n_r
1_____
! Radial velocity
                          !n_phi = 1, n_theta = n_theta_start, n_r
vr(1,n_theta_start,n_r)
                          !n_phi = 2, n_theta = n_theta_start, n_r
vr(2,n_theta_start,n_r)
vr(n_phi_tot,n_theta_start,n_r) !n_phi = n_phi_tot, n_theta = n_theta_start, n_r
```

```
!n_phi = 1, n_theta = n_theta_start+1, n_r
vr(1,n_theta_start+1,n_r)
vr(n_phi_tot,n_theta_start+1,n_r)
vr(1, n_theta_stop, n_r)
                               !n_phi = 1, n_theta = n_theta_stop, n_r
vr(2,n_theta_stop,n_r)
                               !n_phi = 2, n_theta = n_theta_stop, n_r
vr(n_phi_tot,n_theta_stop,n_r)
                               !n_phi = n_phi_tot, n_theta = n_theta_stop, n_r
! Theta component of velocity
vt(1,n_theta_start,n_r)
                               !n_phi = 1, n_theta = n_theta_start, n_r
vt(2,n_theta_start,n_r)
                               !n_phi = 2, n_theta = n_theta_start, n_r
vt(n_phi_tot,n_theta_start,n_r)
                             !n_phi = n_phi_tot, n_theta = n_theta_start, n_r
vt(1,n_theta_start+1,n_r)
                               !n_phi = 1, n_theta = n_theta_start+1, n_r
. . .
vt(n_phi_tot,n_theta_start+1,n_r)
                               !n_phi = 1, n_theta = n_theta_stop, n_r
vt(1,n_theta_stop,n_r)
vt(2,n_theta_stop,n_r)
                               !n_phi = 2, n_theta = n_theta_stop, n_r
vt(n_phi_tot,n_theta_stop,n_r)
                              !n_phi = n_phi_tot, n_theta = n_theta_stop, n_r
! Zonal (phi component) of velocity
1______
                               !n_phi = 1, n_theta = n_theta_start, n_r
vp(1,n_theta_start,n_r)
vp(2,n_theta_start,n_r)
                               !n_phi = 2, n_theta = n_theta_start, n_r
vp(1,n_theta_start+1,n_r)
                              !n_phi = 1, n_theta = n_theta_start+1, n_r
vp(n_phi_tot, n_theta_start+1, n_r)
vp(1,n_theta_stop,n_r)
                               !n_phi = 1, n_theta = n_theta_stop, n_r
                               !n_phi = 2, n_theta = n_theta_stop, n_r
vp(2,n_theta_stop,n_r)
vp(n_phi_tot,n_theta_stop,n_r)
                              !n_phi = n_phi_tot, n_theta = n_theta_stop, n_r
if (l_mag):
                               !Only if it is a magnetic case
! Radial magnetic field
1-----
br(1,n_theta_start,n_r)
                               !n_phi = 1, n_theta = n_theta_start, n_r
br(2,n_theta_start,n_r)
                               !n_phi = 2, n_theta = n_theta_start, n_r
br(n_phi_tot,n_theta_start,n_r) !n_phi = n_phi_tot, n_theta = n_theta_start, n_r
br(1,n_theta_start+1,n_r)
                              !n_phi = 1, n_theta = n_theta_start+1, n_r
br(n_phi_tot,n_theta_start+1,n_r)
```

```
br(1, n_theta_stop, n_r)
                                  !n_phi = 1, n_theta = n_theta_stop, n_r
br(2,n_theta_stop,n_r)
                                  !n_phi = 2, n_theta = n_theta_stop, n_r
. . .
br(n_{phi_tot,n_theta_stop,n_r) !n_{phi} = n_{phi_tot,n_theta} = n_{theta_stop,n_r}
! Theta component of magnetic field
bt(1,n_theta_start,n_r)
                                 !n_phi = 1, n_theta = n_theta_start, n_r
bt(2,n_theta_start,n_r)
                                 !n_phi = 2, n_theta = n_theta_start, n_r
bt(n_phi_tot, n_theta_start, n_r) !n_phi = n_phi_tot, n_theta = n_theta_start, n_r
                                 !n_phi = 1, n_theta = n_theta_start+1, n_r
bt(1,n_theta_start+1,n_r)
bt(n_phi_tot,n_theta_start+1,n_r)
                                 !n_phi = 1, n_theta = n_theta_stop, n_r
bt(1,n_theta_stop,n_r)
                                 !n_phi = 2, n_theta = n_theta_stop, n_r
bt(2,n_theta_stop,n_r)
bt(n_{phi_tot,n_theta_stop,n_r)   !n_{phi} = n_{phi_tot,n_theta} = n_{theta_stop,n_r}
! Zonal (phi component) of magnetic field
bp(1,n_theta_start,n_r)
                                 !n_phi = 1, n_theta = n_theta_start, n_r
bp(2,n_theta_start,n_r)
                                 !n_phi = 2, n_theta = n_theta_start, n_r
bp(n\_phi\_tot, n\_theta\_start, n\_r) \qquad !n\_phi = n\_phi\_tot, n\_theta = n\_theta\_start, n\_r
bp(1,n_theta_start+1,n_r)
                                 !n_phi = 1, n_theta = n_theta_start+1, n_r
bp(n_phi_tot,n_theta_start+1,n_r)
bp(1,n_theta_stop,n_r)
                                  !n_phi = 1, n_theta = n_theta_stop, n_r
bp(2,n_theta_stop,n_r)
                                 !n_phi = 2, n_theta = n_theta_stop, n_r
bp(n_phi_tot,n_theta_stop,n_r)
                                 !n_phi = n_phi_tot, n_theta = n_theta_stop, n_r
!Subsequent blocks
!Block\ N\!+\!1 in both cases have data at the same radial level but the next
!theta chunk (n_theta_start + nThetaB, n_theta_stop + n_thetaB)
!After data for all the theta blocks have been written for one radial
!level, everything above is repeated for the next radial level
```

The graphic files can be read using the python class MagicGraph.

```
>>> G = MagicGraph(ivar = 1, tag='TAG')
```

They can be visualized using the Surf class:

```
>>> S = Surf(tag='TAG')
>>> # Surface map of radial velocity:
>>> S.surf(field = 'vr', r = 0.5, cmap = 'jet', levels = 50)
>>> S.slice(field = 'br', lon_0 = [0]) # Longitudinal Slice of radial magnetic field
>>> S.equat(field = 'entropy') # Equatorial slice of entropy
```

## 8.9 Movie files \* mov. TAG

**Note:** These files are written **only** when  $l\_movie = .true$ . or when a finite number of movie frames are asked for using the input parameters described in the *standard inputs section* of the *output control namelist*.

These are unformatted fortran files containing time evolution of fields on different surfaces - constant radius, colatitude or azimuth or on the full 3D grid. The fields can be of various types like radial magnetic field or velocity, entropy, helicity etc. The type of field and the type of surface can be specified using a string that begins with the field name, followed by the surface type (or 'full 3D', when a 3D movie is desired). One such example is as follows:

```
l_movie = .true.,
n_movie_frames = 1000,
movie(1) = "B r r=0.5",
movie(2) = "V all 3D",
movie(3) = "Hel Eq"
```

The code does not interpret any whitespaces and is not case-sensitive so there's no difference between, say, B r cmb and brcmb. For further details and a list of keywords for different fields and surfaces, please refer to the *movie* in the *output control namelist*.

These files are written by the subroutine write\_movie\_frame.

The movie files are suitably named to reflect the type of field and surface. Their names begin with the keyword for the type of movie asked for, followed by the type of surface, followed by the word 'mov'. Thus, a generic movie name looks like:

```
Keyword_SurType_mov.TAG
```

E.g. if one asks for the radial component of magnetic field on surface of CMB, the movie would be named as Br CMB mov.TAG.

When asks multiple movies for same surface types but different surface levels, the surfaces are numbered with integers. Thus, for the following namelist input,

```
l_movie = .true.,
n_movie_frames = 1000,
movie(1) = "B r r=0.5",
movie(2) = "V p r=0.5",
movie(3) = "V r r=0.8",
```

one would get the following movie files as output:

```
Br_R=C1_mov.TAG
Vp_R=C1_mov.TAG
Vr_R=C2_mov.TAG
```

The structure of a generic movie file is as follows:

```
!-----
! Line 1
!-----
```

```
!Movie version: 'JW_Movie_Version_2'
version
!----
! Line 2
1_____
n_type, n_surface, !Type of movie,
const, n_fields
                              !Type of surface (r,theta,phi,CMB,Eq etc.)
!----
! Line 3
1_____
n_movie_field_type(1:n_fields, n_movie) !Type of fields (velocity,
                                        !mag field, vorticity etc.)
! Line 4
!----
runid
!----
! Line 5
!----
n_r_mov_tot, n_r_max, !Total number of
n_theta_max, n_phi_max, !radial grid points (including IC),
minc, ra, ek, pr, prmag, !grid data, physical parameters
radratio, tScale
!----
! Line 6
r_mov_tot(1:n_r_mov_tot)/r_cmb !All radii in terms of r_CMB
!----
! Line 7
!----
theta(1:n_theta_max) !All theta points
1_____
! Line 8
!----
                     !All phi points
phi(1:n_phi_max)
1-----
! Frame N
!-----
! Line 8 + N
 1_____
```

```
n_frame, t_movie(N), omega_ic, omega_ma, dipLat, dipLon, dipStr, dipStrGeo
! Line 8 + (N+1)
frame_data(1:n_fields,n_start:n_stop) !Desired field data on a
                                     !surface or 3D volume
                                     !n_start = start index of a field
                                     !n\_stop = last index of a field
1_____
! Frame N+1
1_____
! Line 8 + (N+2)
1_____
n_frame, t_movie(N+1), omega_ic, omega_ma, dipLat, dipLon, dipStr, dipStrGeo
! Line 8 + (N+3)
1_____
frame_data(1:n_fields,n_start:n_stop) !Desired field data on a
                                     !surface or 3D volume
                                     !n_start = start index of a field
                                     !n_stop = last index of a field
. . .
! Frame N+M
                                    !M is the desired number of movie frames
1_____
! Line 8 + (N+M)
n_frame, t_movie(N+M), omega_ic, omega_ma, dipLat, dipLon, dipStr, dipStrGeo
1-----
! Line 8 + (N+M)
frame_data(1:n_fields,n_start:n_stop) !Desired field data on a
                                     !surface or 3D volume
                                     !n_start = start index of a field
                                     !n\_stop = last index of a field
```

The 2D movie files can be read and displayed using the python class Movie as follows:

```
>>> Movie() #Lists out available movie files to choose from
>>> M = Movie(file = 'Vr_R=C1_mov.TAG')
```

The 3D movie files can be read using the python class Movie3D:

```
>>> M = Movie3D(file = 'V_3D_mov.TAG')
```

## 8.10 Restart files rst\_\*.TAG

**Note:** These frequency of writing these files are determined by the standard inputs mentioned in the section on *restart files* in the *output control namelist*. If nothing is specified then, by default one restart file is written at the end of the run.

**Note:** A restart file is read **only** when  $l\_start = .true$ .

These are unformatted fortran files containing a snapshot of information about spectral coefficients and physical and grid parameters. As the name suggests, these files are used to 'restart' a run from a specific time. One such file is read by the code at the beginning and are used as initial conditions for the run. These are very useful for continuing a simulation for a long time on computing clusters where the time for a single run is limited.

The file to be read at the beginning is specified by the input parameter *start\_file* which takes in a string providing path to the file.

These files are written by the subroutine store.

The following notations will be used for the coefficients of potentials (note that scalar fields like temperature and pressure do not have a poloidal/toroidal decomposition):

Field	Poloidal	Toroidal
Magnetic	b	aj
Velocity	W	Z
Temperature	S	
Pressure	p	

Time derivatives are denoted with a self-explanatory notation. e.g, dbdt is the first derivative of b.

The word Last appended to a variable name denotes that the value is of the time-step previous to the one during which the file is being written. They are needed for the time-stepping schemes.

\_ic with a variable name says that it belongs to the Inner Core.

```
dsdtLast, dwdtLast, dzdtLast, dpdtLast
else:
! Line 2
  w,z,p
1_____
! Line 3
 dwdtLast, dzdtLast, dpdtLast
if (l_mag):
                                              !If magnetic run
!----
! Line 4
 b, aj, dbdtLast, djdtLast
if(l_mag .and. l_cond_ic):
                                              !If magnetic run
                                              !and conducting inner core
! Line 5
1_____
 b_ic, aj_ic, dbdt_icLast, djdt_icLast
! Line 4 or 5 or 6 depending on 1_mag and 1_cond_ic
lorentz_torque_icLast, lorentz_torque_malast, !Information about torques,
omega_ic1, omegaOsz_ic1, tOmega_ic1, !prescribed rotation and
omega_ic2, omegaOsz_ic2, tOmega_ic2,
                                            !oscillation rates,
omega_ma1, omegaOsz_ma1, tOmega_ma1,
                                            !and the time step-size
omega_ma2, omegaOsz_ma2, tOmega_ma2,
dtNew
```

## 8.11 Poloidal and toroidal potentials at given depths

These are fortran unformatted files which store time series of poloidal and toroidal coefficients of different fields (magnetic field, velocity and temperature) at specific depths.

In the following, time (j) is the time during the  $j^{th}$  time step, time (N) being the last step. real and imag denote real and imaginary parts, respectively, of spherical harmonic coefficients. Also, the following notations will be used for the coefficients of potentials (note that scalar fields like temperature do not have a poloidal/toroidal decomposition):

Field	Poloidal	Toroidal
Magnetic	b	aj
Velocity	W	Z
Temperature	S	

First and second derivatives are denoted with a differential notation. e.g. dw is the first derivative of w, while ddb is the second derivative of b.

#### 8.11.1 B coeff cmb. TAG

**Note:** This file is **only** written when  $l\_cmb\_field=.true$ .

This file contains time series of spherical harmonic coefficients for the poloidal potential of the magnetic field at the outer boundary (CMB) up to a spherical harmonic degree given by  $l\_max\_cmb$ . The detailed calculations are done in the subroutine  $write\_Bcmb$ . The contents of the file look as follows:

- **Header** The file header consists of the information:  $l\_max\_cmb$ , minc and the number of data points  $n\_data$ .
- Data Each chunk of data after the header has the same pattern of time followed by a list of real and imaginary values of coefficients.

Thus, on a whole, the structure of the file looks like follows:

```
>>> # To stack the files B_cmb_coeff.testc to B_cmb_coeff.testf
>>> cmb = MagicCoeffCmb(tag='test[c-f]')
```

```
>>> # print Gauss coefficient for (\ell=10, m=3)
>>> print(cmb.glm[:, 10, 3])
```

#### 8.11.2 Coefficients at desired radii

The following files [B|V|T]\_coeff\_r#.TAG save coefficients at specified depths and are written by the subroutine  $write\_coeff\_r$ . See the section on *CMB* and radial coefficients in the ouput control namelist for details of specifying depth, using  $n\_r\_step$  or  $n\_r\_array$  and desired maximum degree of output  $l\_max\_r$ . A separate file for each desired radius is written, numbered suitably as  $[B|V|T]\_coeff\_r1.TAG$ ,  $[B|V|T]\_coeff\_r2.TAG$  etc.

### 8.11.3 B\_coeff\_r#.TAG

**Note:** This file is **only** written when  $l_r_{field} = .true$ .

This file contains output of time series of the spherical harmonic coefficients of the poloidal and toroidal magnetic field potentials and the first and second derivatives of the poloidal potential coefficients in the order b, db, aj and ddb. The output is for a specific radius, r up to degree  $l\_max\_r$ .

- **Header** The file header consists of the information:  $l\_max\_r$ , minc, the number of data points  $n\_data$  and the radius, r.
- **Data** Each chunk of data after the header contains the time at which the coefficients are stored, followed by the real and imaginary parts of: the poloidal coefficient b, it's first derivative db, the toroidal coefficient a j and the second derivative of the poloidal coefficient ddb.

The complete structure of the file looks like follows:

```
! Line 1
l_max_r, minc, n_data, r
1-----
! Line j + 1
time(j),
real (b(1=1, m=0)), imag(b(1=1, m=0)),
real (b(1=2, m=0)), imag (b(1=2, m=0)),
real(b(l=l_max_cmb, m=l_max_cmb)), imag(b(l=l_max_cmb, m=l_max_cmb)),
real (db(l=1, m=0)), imag(db(l=1, m=0)),
real (db(1=2, m=0)), imag(db(1=2, m=0)),
real (db(l=1_max_cmb, m=1_max_cmb)), imag(db(l=1_max_cmb, m=1_max_cmb)),
real (aj(l=1, m=0)), imag(aj(l=1, m=0)),
real (aj(1=2, m=0)), imag(aj(1=2, m=0)),
real(aj(l=1_max_cmb, m=1_max_cmb)), imag(aj(l=1_max_cmb, m=1_max_cmb)),
real (ddb (l=1, m=0)), imag (ddb (l=1, m=0)),
real (ddb(1=1, m=0)), imag(ddb(1=1, m=0)),
```

```
real(ddb(l=l_max_cmb, m=l_max_cmb)), imag(ddb(l=l_max_cmb, m=l_max_cmb)),
. . .
! Line N + 1
time(N),
real (b(1=1, m=0)), imag(b(1=1, m=0)),
real (b (1=2, m=0)), imag (b (1=2, m=0)),
real (db(1=1, m=0)), imag(db(1=1, m=0)),
real (db(1=2, m=0)), imag(db(1=2, m=0)),
real (aj(l=1, m=0)), imag(aj(l=1, m=0)),
real (aj(1=2, m=0)), imag(aj(1=2, m=0)),
real (aj(l=l_max_cmb, m=l_max_cmb)), imag(aj(l=l_max_cmb, m=l_max_cmb)),
real (ddb(1=0, m=0)), imag(ddb(1=0, m=0)),
real (ddb (l=1, m=0)), imag (ddb (l=1, m=0)),
real (ddb(l=l_max_cmb, m=l_max_cmb)), imag(ddb(l=l_max_cmb, m=l_max_cmb))
```

This file can be read using MagicCoeffR with the following options:

```
>>> # To stack the files B_coeff_r3.test* from the working directory
>>> cr = MagicCoeffR(tag='test*', field='B', r=3)
>>> # print the time and the poloidal potential for (\ell=3, m=3)
>>> print(cr.time, cr.wlm[:, 3, 3])
```

#### 8.11.4 V\_coeff\_r#.TAG

**Note:** This file is **only** written when  $l_r_{field}$ =.true.

This file contains output of time series of the spherical harmonic coefficients of the poloidal and toroidal velocity field potentials and the first derivatives of the poloidal potential coefficients in the order w, dw, and z. The output is for a specific radius, r up to degree  $l\_max\_r$ .

- **Header** The file header consists of the information:  $l\_max\_r$ , minc, the number of data points  $n\_data$  and the radius, r.
- Data Each chunk of data after the header contains the time at which the coefficients are stored, followed by the real and imaginary parts of: the poloidal coefficient w, it's first derivative dw and the toroidal coefficient z.

The complete structure of the file looks like follows:

```
!------
! Line 1
!------
!------
l_max_r, minc, n_data, r
```

```
!-----
! Line j + 1
time(j),
real (w(l=1, m=0)), imag (w(l=1, m=0)),
real (w(1=2, m=0)), imag (w(1=2, m=0)),
real(w(l=l_max_cmb, m=l_max_cmb)), imag(w(l=l_max_cmb, m=l_max_cmb)),
real (dw(l=1, m=0)), imag (dw(l=1, m=0)),
real (dw(1=2, m=0)), imag(dw(1=2, m=0)),
real(dw(l=1_max_cmb, m=1_max_cmb)), imag(dw(l=1_max_cmb, m=1_max_cmb)),
real (z(1=1, m=0)), imag(z(1=1, m=0)),
real (z(1=2, m=0)), imag(z(1=2, m=0)),
real(z(l=1_max_cmb, m=1_max_cmb)), imag(z(l=1_max_cmb, m=1_max_cmb)),
! Line N + 1
time(N).
real (w(l=1, m=0)), imag(w(l=1, m=0)),
real (w(1=2, m=0)), imag (w(1=2, m=0)),
real (w(l=1_max_cmb, m=1_max_cmb)), imag(w(l=1_max_cmb, m=1_max_cmb)),
real (dw (l=1, m=0)), imag (dw (l=1, m=0)),
real (dw(1=2, m=0)), imag(dw(1=2, m=0)),
real (dw(l=1_max_cmb, m=1_max_cmb)), imag(dw(l=1_max_cmb, m=1_max_cmb)),
real (z(1=1, m=0)), imag(z(1=1, m=0)),
real (z(1=2, m=0)), imag(z(1=2, m=0)),
real(z(l=l_max_cmb, m=l_max_cmb)), imag(z(l=l_max_cmb, m=l_max_cmb))
```

This file can be read using MagicCoeffR with the following options:

```
>>> # To stack the files V_coeff_r3.test* from the working directory
>>> cr = MagicCoeffR(tag='test*', field='V', r=3)
>>> # print the poloidal and toroidal potentials for (\ell=6, m=0)
>>> print(cr.wlm[:, 6, 0], cr.zlm[:, 6, 0])
```

#### 8.11.5 T\_coeff\_r#.TAG

**Note:** This file is **only** written when  $l_r_{field}T = .true$ .

This file contains output of time series of the spherical harmonic coefficients of the temperature (or entropy) field. The output is for a specific radius, r up to degree  $l\_max\_r$ .

• **Header** The file header consists of the information:  $l\_max\_r$ , minc, the number of data points  $n\_data$  and the radius, r.

• **Data** Each chunk of data after the header contains the time at which the coefficients are stored, followed by the real and imaginary parts of the coefficient s.

The complete structure of the file looks like follows:

```
! Line 1
l_max_r, minc, n_data, r
1______
!-----
! Line j + 1
time(j),
real (s(1=0, m=0)), imag(s(1=0, m=0)),
real (s(l=1, m=0)), imag(s(l=1, m=0)),
real (s(1=2, m=0)), imag(s(1=2, m=0)),
real(s(l=1_max_cmb, m=1_max_cmb)), imag(s(l=1_max_cmb, m=1_max_cmb)),
! Line N + 1
1-----
time(N),
real (s(1=0, m=0)), imag(s(1=0, m=0)),
real (s(l=1, m=0)), imag(s(l=1, m=0)),
real (s(1=2, m=0)), imag(s(1=2, m=0)),
real(s(l=l_max_cmb, m=l_max_cmb)), imag(s(l=l_max_cmb, m=l_max_cmb)),
```

## 8.12 TO outputs

**Note:** These output files are **only** written when  $l\_TO=.true$ .

#### 8.12.1 TOZ #.TAG and TOZM.TAG

#### 8.12.2 TO\_mov.TAG files

**Note:** This file is **only** written when  $l\_TOmovie = .true$ .

This file contains the time evolution of the different forces that enter the phi-average of the azimuthal component of the Navier-Stokes equation. This is a special kind of *movie file* that contains seven different azimuthally-averaged fields in a  $(r,\theta)$  plane: the axisymmetric zonal flow component, the azimuthal component of the Reynolds stresses, the azimuthal component of advection, the azimuthal component of viscosity, the azimuthal component of Lorentz force, the azimuthal component of Coriolis force and the azimuthal component of the time-derivative. The structure of the

file is similar to a *movie file*, i.e. an unformatted fortran binary file with a header that describes the type of the movie file. The detailed calculations can be found in the subroutine out TO.

On a whole, the structure of the file looks like follows:

```
! Line 1
version
!-----
! Line 2
n_type, n_surface, const, n_fields
!----
! Line 3
!-----
runid
!-----
! Line 4
!----
n_r_movie_max, n_r_max, n_theta_max, n_phi_tot, minc, ra, ek, pr,
prmag, radratio, tScale
! Line 5
r(1), r(2), ..., r(n_r_movie_max)
1_____
! Line 6
!----
theta(1), theta(2), ..., theta(n_{theta_max})
1_____
! Line 7
!----
phi(1), phi(2), ..., phi(n_theta_max)
!-----
! Line 7+N
n_frame, t_movie(N), omega_ic, omega_ma, dipLat, dipLon, dipStr, dipStrGeo
! Line 7+(N+1)
```

8.12. TO outputs 101

This file can be read using TOMovie with the following options:

```
>>> # To load 'TO_mov.test' and time-average it:
>>> to = TOMOvie(file='TO_mov.test', avg=True, levels=65, cm='seismic')
```

## 8.13 Radial spectra rB[r|p]Spec.TAG

**Note:** This files are **only** written when  $l_rMagSpec = .true$ .

Those files contain the time-evolution of the poloidal (**rBrSpec.TAG**) and the toroidal (**rBpSpec.TAG**) magnetic energies for all radii including the inner core and for spherical harmonic degrees from  $\ell=1$  to  $\ell=6$ . The calculations are done in the subroutines rBrSpec and rBpSpec, respectively. The outputs are stored as a fortran unformatted file which follows the following structure for rBrSpec. TAG:

The rBpSpec.TAG files have exactly the same structure (just replacing the poloidal energy by its toroidal counterpart).

**Warning:** Be careful that in this file,  $n_r_t$  is the **total** number of grid points (thus including the inner core).

Those files can be read using the python class MagicRSpec with the following options:

```
>>> # Read the files BrSpec.testa, BrSpec.testb and BrSpec.testc and stack them
>>> rsp = MagicRSpec(tag='test[a-c]', field='Br')
>>> # Print time and the time evolution of e_pol(\ell=4) at the 10th radial grid point
>>> print(rsp.time, rsp.e_pol[:, 10, 3])
```

## 8.14 Potential files [V|B|T]pot\_#.TAG

## 8.14.1 Vpot\_#.TAG and Vpot\_ave.TAG

**Note:** These output files are **only** written when either when  $l\_storePot=.true$ . or when  $l\_storeVpot=.true$ .

These files contain a snapshot of the poloidal and toroidal flow potentials w and z in the Chebyshev space for all spherical harmonic degrees and orders. They basically contain two arrays of dimension ( $lm_max$ ,  $n_cheb_max$ ). The detailed calculations are done in the subroutine storePot. The outputs are stored as a fortran unformatted file which follows the following structure:

#### 8.14.2 Bpot\_#.TAG, Bpot\_ave.TAG

**Note:** These output files are **only** written when either when  $l\_storePot=.true$ . or when  $l\_storeBpot=.true$ .

These files contain a snapshot of the poloidal and toroidal magnetic potentials b and a j in the Chebyshev space for all spherical harmonic degrees and orders. The detailed calculations are done in the subroutine storePot. The outputs are stored as a fortran unformatted file which follows the following structure:

```
! Line 1
1-----
l_max, n_cheb_max, n_cheb_ic_max, minc, lm_max ! Header (truncation)
!----
! Line 2
1-----
ra, ek, pr, prmag, sigma_ratio, omega_ma, omega_ic ! Header (physics)
! Line 3
!-----
                                           ! Time and poloidal potential
b(lm=1,n_cheb=1), b(lm=2, n_cheb=1), ..., b(lm=lm_max, n_cheb=1),
b(lm=1,n_cheb=n_cheb_max, ..., b(lm=lm_max,n_cheb=n_cheb_max)
1_____
! Line 4
                                          ! Time and toroidal potential
aj(lm=1,n_cheb=1), aj(lm=2, n_cheb=1), ..., aj(lm=lm_max, n_cheb=1),
aj(lm=1,n_cheb=n_cheb_max, ..., aj(lm=lm_max,n_cheb=n_cheb_max)
! The two following lines are optional and are only written when there is !
! an electrically-conducting inner-core
!----
! Line 5
```

## 8.14.3 Tpot\_#.TAG, Tpot\_ave.TAG

**Note:** These output files are **only** written when either when  $l\_storePot=.true$ . or when  $l\_storeTpot=.true$ .

These files contain a snapshot of the temperature/entropy s in the spectral and Chebyshev spaces for all spherical harmonic degrees and orders. They basically contain one array of dimension ( $lm_max$ ,  $n_cheb_max$ ). The detailed calculations are done in the subroutine storePot. The outputs are stored as a fortran unformatted file which follows the following structure:

**CHAPTER** 

**NINE** 

## DATA VISUALISATION AND POST-PROCESSING

Most of the *output files* written during a run of MagIC can be treated with the python post-processing classes and functions present in the \$MAGIC\_HOME/python/magic directory. These classes depend on several python libraries that can be usually found in most of the Linux distributions.

# 9.1 Requirements

## 9.1.1 Hard dependencies

- python 2.7/3.3 or higher.
- matplotlib 1.0 or higher.
- scipy 0.10 or higher.

## 9.1.2 Optional dependencies

- Although entirely optional, the installation of ipython makes the interactive use of the post-processing python functions much more pleasant. Installing it is therefore recommanded for a smoother interactive usage of the python functions.
- The installation of the basemap toolkit is optional. If installed, additional projections for the magic.Surf (Aitoff, orthographic, Mollweide, etc.) class will be provided for 2-D surface plotting. Otherwise, the usage of magic.Surf is limited to the Hammer projection.

# 9.2 Configuration: magic.cfg file

A file named magic.cfg located in \$MAGIC\_HOME/python/magic.cfg should have been created when you used the source path/sourceme.sh command for the first time on your machine. At that stage, it tried to automatically fill the best options that correspond to your setup. Although tested on several various machine configurations, the auto-configuration script might however fail on your setup. The paragraph below details the possible options that you may want to adjust in the magic.cfg file.

## 9.2.1 Detailed options

In case, the file magic.cfg doesn't exist in the directory \$MAGIC\_HOME/python/magic, you can easily copy it from the default configuration magic.cfg.default and then adjust the options manually:

```
$ cp $MAGIC_HOME/python/magic/magic.cfg.default $MAGIC_HOME/python/magic/magic.cfg
```

In that file, you can set up the default matplotlib rendering backend (among the possible options: TkAgg, GTKAgg, Qt4Agg, ...). The default configuration is

```
backend = TkAgg
```

Note: This is usually the default configuration which is the most likely to work on supercomputing clusters.

If LaTeX is installed on your work station, you might also want to make use of the better looking LaTeX fonts for all your displayed matplotlib figures (labels, caption, ticks, etc.). Be careful though that most of the time LaTeX is **not installed** on supercomputers. The default configuration is thus:

```
labTex = False
```

If you want to enable all the features of the python functions (faster reading the  $G_{-}\#.TAG$ , conversion to the VTK/VTS file format, potential extrapolation of the field lines, etc.), some fortran libraries present in the  $$MAGIC_{-}HOME/python/magic/fortranLib$$  directory need to be built using the f2py, which should be available on your Linux workstation if all the required python libraries have been correctly installed. The boolean buildlib can control whether you want to try building the fortran libraries with f2py. The following configuration will try to build the libraries:

```
buildLib = True
```

The exact name of the executable f2py however varies from one Linux distribution to the other. Among possible options, one frequently finds: f2py, f2py3. This can be set to your proper configuration using the f2pyexec option of the magic.cfg file. The default configuration is:

```
f2pyexec = f2py2
```

You can also choose the fortran compiler you want to use on your machine. A list of the installed compilers can be obtained by using (where £2py has to be replaced by your own executable):

```
$ f2py -c --help-fcompiler
```

The most frequent options are:

- gnu95 for the GNU gfortran compiler.
- intelem for the Intel ifort compiler.
- pg for the Portlang group pgf compiler.

Once you've decided the ideal configuration for your machine, set it up via the option fcompiler:

```
fcompiler = intelem
```

Finally, he same configuration procedure can be applied to the C compiler using the variable named ccompiler. The possible options are:

- unix for the GNU gcc compiler.
- intelem for the Intelicc compiler.

In most of the configurations, the default configuration should do a good job:

```
ccompiler = unix
```

If you encounter any problem during the building stage, you can try playing with this parameter though.

## 9.2.2 Ready?!

Once you think you set up your magic.cfg file correctly, you can test your configuration. If you decided to build the fortran libraries (i.e. buildLib=True), you can easily test it with any python shell by typing the following command:

```
>>> from magic import *
```

If the build was successful, it should display:

```
Please wait: building greader_single...
Please wait: building greader_double...
Please wait: building potential extrapolation...
Please wait: building vtklib...
```

Once the libraries have been successfully installed, this message won't be displayed again, except if you remove the \*.so files that are now present in the \$MAGIC\_HOME/python/magic/directory.

# 9.3 Python functions and classes

Once the python environment is correctly configured you can use the available functions and classes to analyse and post-process your data. The following pages will give you the detailed API of the available classes, as well as some practical examples:

#### Python classes

- 1. To read the **log.TAG** files, see *here*.
- 2. To read and analyse the time series, see *here*.
- 3. To read and analyse the radial profiles, see *here*.
- 4. To read and analyse spectra spec #.TAG, see here.
- 5. To read and analyse the **G\_#.TAG** files, see *here*.
- 6. To read and analyse movie files **\_mov.TAG**, see *here*.
- 7. To read and analyse coeff files **\_coeff.TAG**, see *here*.
- 8. To read and analyse coeff files **coeff.TAG**, see *here*.
- 9. To read and analyse radial spectra B[r|p]Spec.TAG, see *here*.
- 10. To compare several runs simultaneously, see *here*.
- 11. For additional diagnostics (boundary layer, heat transport, interpolation on cylindrical grids, etc.), see *here*.
- 12. To take a look at the additional useful functions available (derivation, integration, interpolation, etc.), see *here*.

# 9.3.1 Support for the log. TAG files

class magic.MagicSetup (datadir='.', nml='input.nml', quiet=False)

This class allows to read the input namelist or the log file of a current job and creates an object that contains all the parameters found in the namelist/log file.

```
>>> stp = MagicSetup(nml='log.test', quiet=True)
>>> print(stp.ra) # print the Rayleigh number
>>> print(stp.n_r_max) # print n_r_max
```

```
___init__ (datadir='.', nml='input.nml', quiet=False)
```

#### **Parameters**

- datadir (str) the working directory
- nml (str) name of the input namelist/ log file
- quiet (bool) when set to True, makes the output silent (default False)

```
weakref
```

list of weak references to the object (if defined)

## 9.3.2 Support for the time series

```
class magic. MagicTs (datadir='.', field='e_kin', iplot=True, all=False, tag=None)

This python class is used to read and plot the different time series written by the code:
```

•Kinetic energy: *e\_kin.TAG* 

•Magnetic energy of the outer core:  $e_mag_oc.TAG$ 

•Magnetic energy of the inner core: *e\_mag\_ic.TAG* 

•Dipole information: dipole.TAG

•Rotation: rot.TAG

•Diagnostic parameters: par.TAG

•Miscellaneous: misc.TAG

• Velocity square: *u\_square.TAG* 

•Angular momentum: AM.TAG

•Power budget: power.TAG

•Parallel and perpendicular decomposition: perpPar.TAG

•RMS force balance: dtVrms.TAG

•RMS induction terms: dtBrms.TAG

Here are a couple of examples of how to use this function.

```
>>> # plot the most recent e_kin.TAG file found in the directoy
>>> MagicTs(field='e_kin')
>>>
>>> # stack **all** the power.TAG file found in the directory
>>> ts = MagicTs(field='power', all=True)
>>> print(ts.time, ts.buoPower) # print time and buoyancy power
>>>
>>> # If you only want to read the file ``misc.NOm2z``
>>> ts = MagicTs(field='misc', tag='NOm2z', iplot=False)
```

```
__init__ (datadir='.', field='e_kin', iplot=True, all=False, tag=None)
```

- field(str) the file you want to plot
- **iplot** (*bool*) when set to True, display the plots (default True)
- **all** (*bool*) when set to True, the complete time series is reconstructed by stacking all the corresponding files from the working directory (default False)
- tag (str) read the time series that exactly corresponds to the specified tag

```
plot()
```

Plotting subroutines. Only called if 'iplot=True'

## 9.3.3 Averaging the time series

class magic . AvgField (tstart=None, tag=None, dipExtra=False)

This class calculates the time-average properties from time series. It will store the input starting time in a small file named tInitAvg, such that the next time you use it you don't need to give tstart again.

```
>>> # Average from t=2.11 and also store the additional dipole.TAG informations
>>> a = AvgField(tstart=2.11, dipExtra=True)
>>> # Average only the files that match the pattern N0m2[a-c]
>>> a = AvgField(tstart=2.11, tag='N0m2[a-c]')
>>> # Average only the files that match the pattern N0m2Z*
>>> a = AvgField(tstart=2.11, tag='N0m2Z*')
>>> print(a) # print the formatted output
```

```
___init___(tstart=None, tag=None, dipExtra=False)
```

#### **Parameters**

- **tstart** (*float*) the starting time for averaging
- tag (str) if you specify an input tag (generic regExp pattern), the averaging process will only happen on the time series that match this input pattern
- **dipExtra** (*bool*) if this parameter is set to True, then additional values extracted from *dipole.TAG* are also computed

```
__str__()
Formatted output
__weakref__
list of weak references to the object (if defined)
```

## 9.3.4 Support for time-averaged radial profiles

**class** magic.**MagicRadial** (datadir='.', field='eKin', iplot=True, tag=None, tags=None)

This class can be used to read and display the time and horizontally averaged files:

```
•Kinetic energy: eKinR.TAG
•Magnetic energy: eMagR.TAG
```

•Anelastic reference state: anel.TAG

•Variable electrical conductivity: varCond.TAG

•Variable thermal diffusivity: varDiff.TAG

• Variable kinematic viscosity: varVisc.TAG

•Diagnostic parameters: parR.TAG

•Power budget: powerR.TAG

•Heat fluxes: fluxesR.TAG

•Radial profiles used for boundary layers: bLayersR.TAG

•Parallel/perpendicular decomposition: perpParR.TAG

```
>>> rad = MagicRadial(field='eKinR') # display the content of eKinR.tag
>>> print(rad.radius, rad.ekin_pol_axi) # print radius and poloidal energy
```

\_\_init\_\_ (datadir='.', field='eKin', iplot=True, tag=None, tags=None)

#### **Parameters**

- **field** (str) the field you want to plot
- **iplot** (*bool*) to plot the output, default is True
- tag (str) a specific tag, default is None
- **tags** (*list*) a list that contains multiple tags: useful to sum several radial files

#### plot()

Display the result when iplot=True

## 9.3.5 Support for the spectra files (kin|mag|u2)\_spec\_#.TAG

This class can be used to read and display the spectra:

- •Kinetic energy spectra: kin\_spec\_#.TAG
- •Magnetic energy spectra: mag\_spec\_#.TAG
- •Spectra of the velocity square: u2\_spec\_#.TAG

```
>>> # display the content of kin_spec_1.tag
>>> # where tag is the most recent file in the current directory
>>> sp = MagicSpectrum(field='e_kin', ispec=1)
>>> # display the content of mag_spec_ave.test on one single figure
>>> sp = MagicSpectrum(field='e_mag', tag='test', ave=True, gather=True)
```

init (datadir='.', field='e kin', iplot=True, ispec=None, ave=False, gather=False, tag=None)

#### **Parameters**

- **field** (*str*) the spectrum you want to plot, 'e\_kin' for kinetic energy, 'e\_mag' for magnetic
- **iplot** (*bool*) display the output plot when set to True (default is True)
- **ispec** (*int*) the number of the spectrum you want to plot
- tag (str) file suffix (tag), if not specified the most recent one in the current directory is chosen
- ave (bool) plot a time-averaged spectrum when set to True
- **gather** (*bool*) gather the spectra on the same figure when set to True, display one figure per spectrum when set to False, (default is False)
- datadir (str) current working directory

### plot()

Plotting function

## 9.3.6 Support for the 2-D spectra files

This class can be used to read and display 2-D spectra in the  $(r, \ell)$  and in the (r, m) planes

- •Kinetic energy spectra: 2D\_kin\_spec\_#.TAG
- •Velocity square spectra: 2D\_u2\_spec\_#.TAG
- •Magnetic energy spectra: 2D\_mag\_spec\_#.TAG

```
>>> # display the content of 2D_kin_spec_1.tag
>>> # where tag is the most recent file in the current directory
>>> sp = MagicSpectrum2D(field='e_kin', ispec=1, levels=17, cm='seismic')
>>> # display the content of 2D_mag_spec_3.test
>>> sp = MagicSpectrum2D(field='e_mag', tag='test', ispec=3)
```

\_\_init\_\_ (datadir='.', field='e\_mag', iplot=True, ispec=None, tag=None, cm='jet', levels=33, precision='Float64')

#### **Parameters**

- field (str) the spectrum you want to plot, 'e\_kin' for kinetic energy, 'e\_mag' for magnetic
- **iplot** (*bool*) display the output when set to True (default is True)
- ispec (int) the number of the spectrum you want to plot
- tag (str) file suffix (tag=, if not specified the most recent one in the current directory is chosen
- **cm** (*str*) name of the colormap (default='jet')
- **levels** (*int*) number of contour levels (default 33)
- precision (str) single or double precision
- datadir (str) current working directory

plot (*levels*, *cm*)
Plotting function

#### **Parameters**

- **levels** (*int*) number of contour levels
- cm(str) name of the colormap

## 9.3.7 Support for G\_#.TAG files

class magic. MagicGraph (ivar=None, datadir='.', format='B', quiet=True, ave=False, tag=None, precision='Float32')

This class allows to read the 3-D graphic outputs of the MagIC code (*G\_#.TAG* and *G\_*ave.TAG) files. Those are binary unformatted outputs, there are therefore two ways to load them:

- •If buildLib=True in magic.cfg and the fortran libraries were correctly built, then the reader uses a fortran program that is expected to be much faster than the pure python routine.
- •If buildLib=False, then a pure python program is used to read the G files.

```
>>> # Regular G files
>>> gr = MagicGraph(ivar=1, tag='N0m2a')
>>> print(gr.vr.shape) # shape of vr
>>> print(gr.ek) # print ekman number
>>> print(gr.minc) # azimuthal symmetry
>>> # Averaged G file with double precision
>>> gr = MagicGraph(ave=True, tag='N0m2', precision='Float64')
```

\_\_init\_\_(ivar=None, datadir='.', format='B', quiet=True, ave=False, tag=None, precision='Float32')

#### **Parameters**

- **format** (*str*) format of binary output: 'n' (native), 'B' (big endian) or 'l' (little endian), (default 'B')
- **ave** (*bool*) when set to True, it tries to find an average G file (G\_ave.TAG)
- ivar (int) the number of the G file
- tag (str) extension TAG of the G file. If not specified, the most recent G\_#.TAG file found in the directory will be selected.
- quiet (bool) when set to True, makes the output silent
- datadir (str) directory of the G file (default is . )
- **precision** (*str*) single or double precision (default 'Float32')

## rearangeLat (field)

This function is used to unfold the colatitudes

**Parameters field** (*numpy.ndarray*) – input array with MagIC ordering of colatitudes (i.e. successively Northern Hemisphere and Southern Hemisphere)

**Returns** an array with the regular ordering of the colatitudes

**Return type** numpy.ndarray

**class** magic. **Surf** (*ivar=None*, *datadir='.'*, *vort=False*, *ave=False*, *tag=None*, *precision='Float32'*)

This class allows to display the content of a graphic file (*G\_#.TAG* or *G\_ave.TAG*). It allows to plot radial, azimuthal and equatorial cuts as well as phi-averages.

```
>>> # To read G_1.test
>>> s = Surf(ivar=1, ave=False, tag='test')
>>> # To read the latest G file in the working directory (double precision)
>>> s = Surf(precision='Float64')
```

```
>>> # Possible plots
>>> s.equat(field='vr')
>>> s.avg(field='vp')
>>> s.surf(field='entropy', r=0.8)
>>> s.slice(field='Br', lon_0=[0, 30])
```

\_\_init\_\_ (ivar=None, datadir='.', vort=False, ave=False, tag=None, precision='Float32')

- ivar (int) index of the graphic file
- ave (bool) when set to True, it tries to read a time-averaged graphic file
- tag (str) TAG suffix extension of the graphic file

- **vort** (*bool*) a boolean to specify whether one wants to compute the 3-D vorticity components (take care of the memory imprint)
- datadir (str) the working directory
- **precision** (*str*) the storage precision of the graphic file (single or double precision). Default is 'Float32' (single)

## \_\_weakref\_

list of weak references to the object (if defined)

avg (field='vphi', levels=16, cm='RdYlBu\_r', normed=True, vmax=None, vmin=None, cbar=True, tit=True, pol=False, tor=False, mer=False, merLevels=16, polLevels=16)
Plot the azimutal average of a given field.

```
>>> s = Surf()
>>> # Axisymmetric zonal flows, 65 contour levels
>>> s.avg(field='vp', levels=65, cm='seismic')

>>> # Minimal plot (no cbar, not title)
>>> s.avg(field='Br', tit=False, cbar=False)

>>> # Axisymmetric Bphi + poloidal field lines
>>> s.avg(field='Bp', pol=True, polLevels=8)

>>> # Omega-effect, contours truncated from -1e3 to 1e3
```

#### **Parameters**

• field (str) - the field you want to display

>>> s.avg(field='omeffect', vmax=1e3, vmin=-1e3)

- **levels** (*int*) the number of levels in the contourf plot
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- ullet title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- **vmax** (*float*) maximum value of the contour levels
- **vmin** (*float*) minimum value of the contour levels
- **normed** (*bool*) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.
- pol (bool) diplay the poloidal field lines contours when set to Tru
- mer (bool) display the meridional circulation contours when set to True
- merLevels (int) number of contour levels to display meridional circulation
- pollevels (int) number of contour levels to display poloidal field lines

equat (field='vr', levels=16, cm='RdYlBu\_r', normed=True, vmax=None, vmin=None, cbar=True, tit=True, avg=False, normRad=False)
Plot the equatorial cut of a given field

```
>>> s = Surf()
>>> # Equatorial cut of the z-vorticity, 65 contour levels
>>> s.equat(field='vortz', levels=65, cm='seismic')
```

```
>>> # Minimal plot (no cbar, not title)
>>> s.equat(field='bphi', tit=False, cbar=False)

>>> # Control the limit of the colormap from -1e3 to 1e3
>>> s.equat(field='vr', vmin=-1e3, vmax=1e3, levels=33)

>>> # Normalise the contour levels radius by radius
>>> s.equat(field='jphi', normRad=True)
```

#### **Parameters**

- **field** (*str*) the name of the input physical quantity you want to display
- **avg** (*bool*) when set to True, an additional figure which shows the radial profile of the input physical quantity (azimuthal average) is also displayed
- **normRad** (*bool*) when set to True, the contour levels are normalised radius by radius (default is False)
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- tit (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (*float*) minimum value of the contour levels
- **normed** (*bool*) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

slice (field='Bphi', lon\_0=0.0, levels=12, cm='RdYlBu\_r', normed=True, vmin=None, vmax=None, cbar=True, tit=True, grid=False, nGridLevs=16)
Plot an azimuthal slice of a given field.

```
>>> s = Surf()
>>> # vphi at 0, 30, 60 degrees in longitude
>>> s.slice(field='vp', lon_0=[0, 30, 60], levels=65, cm='seismic')
```

```
>>> # Minimal plot (no cbar, not title)
>>> s.avg(field='vp', lon_0=32, tit=False, cbar=False)
```

```
>>> # Axisymmetric Bphi + poloidal field lines
>>> s.avg(field='Bp', pol=True, polLevels=8)
```

```
>>> # Omega-effect, contours truncated from -1e3 to 1e3
>>> s.avg(field='omeffect', vmax=1e3, vmin=-1e3)
```

- **field** (*str*) the field you want to display
- 1on 0 (float or list) the longitude of the slice in degrees, or a list of longitudes
- **levels** (*int*) the number of levels in the contourf plot
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- tit (bool) display the title of the figure when set to True

- cbar (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (*float*) minimum value of the contour levels
- grid (bool) display or hide the grid
- nGridLevs (int) number of grid levels

surf (field='Bphi', proj='hammer', lon\_0=0.0, r=0.85, vmax=None, vmin=None, lat\_0=30.0, levels=16, cm='RdYlBu\_r', normed=True, cbar=True, tit=True, lines=False)
Plot the surface distribution of an input field at a given input radius (normalised by the outer boundary radius).

```
>>> s = Surf()
>>> # Radial flow component at ``r=0.95 r_o``, 65 contour levels
>>> s.surf(field='vr', r=0.95, levels=65, cm='seismic')

>>> # Minimal plot (no cbar, not title)
>>> s.surf(field='entropyfluct', r=0.6, tit=False, cbar=False)

>>> # Control the limit of the colormap from -1e3 to 1e3
>>> s.surf(field='vp', r=1., vmin=-1e3, vmax=1e3, levels=33)

>>> # If basemap is installed, additional projections are available
>>> s.surf(field='Br', r=0.95, proj='ortho', lat_0=45, lon_0=45)
```

#### **Parameters**

- **field** (*str*) the name of the field you want to display
- **proj** (*str*) the type of projection. Default is Hammer, in case you want to use 'ortho' or 'moll', then Basemap is required.
- **r** (*float*) the radius at which you want to display the input data (in normalised units with the radius of the outer boundary)
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- tit (bool) display the title of the figure when set to True
- **cbar** (*bool*) display the colorbar when set to True
- **lines** (*bool*) when set to True, over-plot solid lines to highlight the limits between two adjacent contour levels
- vmax (float) maximum value of the contour levels
- **vmin** (*float*) minimum value of the contour levels
- **normed** (*bool*) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

## 9.3.8 Support for movie files \*\_mov.TAG

```
>>> m = Movie()
>>> # This returns a list of the available movies in the directory
>>> # and lets you decide which one you want to read
```

```
>>> # Reads and display AV_mov.test
>>> m = Movie(filed='AV_mov.test')
>>> print(m.data) # access to the data
```

```
>>> # Read three movie files (no display)
>>> m1 = Movie(file='AV_mov.testa', iplot=True)
>>> m2 = Movie(file='AV_mov.testb', iplot=True)
>>> m3 = Movie(file='AV_mov.testc', iplot=True)
>>> # Stack them together
>>> m = m1+m2+m3
>>> # Display
>>> m.plot(levels=33, cm='seismic', cut=0.5)
```

```
>>> # Store the outputs in movie/img_#.png
>>> # Only from the timesteps 280 to 380
>>> m = Movie(file='AB_mov.test', png=True, nvar=100, lastvar=380)
```

\_\_\_add\_\_\_(new)

Built-in function to sum two movies

**Note:** So far this function only works for two movies with the same grid sizes. At some point, we might introduce grid extrapolation to allow any summation/

\_\_init\_\_ (file=None, iplot=True, step=1, png=False, lastvar=None, nvar='all', levels=12, cm='RdYlBu\_r', cut=0.5, bgcolor=None, fluct=False, normed=False, avg=False, std=False, dpi=80, normRad=False, precision='Float32')

- **nvar** (*int*) the number of timesteps of the movie file we want to plot starting from the last line
- png (bool) if png=True, write the png files instead of display
- iplot (bool) if iplot=True, display otherwise just read
- lastvar (int) the number of the last timesteps to be read
- **step** (*int*) the stepping between two timesteps
- **levels** (*int*) the number of contour levels
- cm (str) the name of the color map
- **fluct** (*bool*) if fluct=True, substract the axisymmetric part
- **normed** (*bool*) the colormap is rescaled every timestep when set to True, otherwise it is calculated from the global extrema
- avg (bool) if avg=True, time-average is displayed
- **std** (*bool*) if std=True, standard deviation is displayed
- **dpi** (*int*) dot per inch when saving PNGs
- normRad (bool) if normRad=True, then we normalise for each radial level
- **precision** (*str*) precision of the input file, Float32 for single precision, Float64 for double precision

- **cut** (*float*) adjust the contour extrema to max(abs(data))\*cut
- **bgcolor** (*str*) background color of the figure

### \_\_weakref\_

list of weak references to the object (if defined)

avgStd (std=False, cut=0.5, levels=12, cmap='RdYlBu\_r') plot time-average or standard deviation

#### **Parameters**

- std (bool) the standard deviation is computed instead the average when std is True
- **levels** (*int*) number of contour levels
- cmap (str) name of the colormap
- cut (float) adjust the contour extrema to max(abs(data))\*cut

#### **Parameters**

- **levels** (*int*) number of contour levels
- cmap (str) name of the colormap
- cut (float) adjust the contour extrema to max(abs(data))\*cut
- png (bool) save the movie as a series of png files when set to True
- **dpi** (*int*) dot per inch when saving PNGs
- **bgcolor** (*str*) background color of the figure
- **normed** (*bool*) the colormap is rescaled every timestep when set to True, otherwise it is calculated from the global extrema
- **step** (*int*) the stepping between two timesteps

class magic.Movie3D (file=None, step=1, lastvar=None, nvar='all', nrout=48, ratio\_out=2.0, extrapot=False, precision='Float32')

This class allows to read the 3D movie files  $(B|V)_3D_-.TAG$  and transform them into a series of VTS files ./vtsFiles/B3D\_#.TAG that can be further read using paraview.

```
>>> Movie3D(file='B_3D.TAG')
```

\_\_init\_\_ (file=None, step=1, lastvar=None, nvar='all', nrout=48, ratio\_out=2.0, extrapot=False, precision='Float32')

- **file** (*str*) file name
- nvar (int) the number of timesteps of the movie file we want to plot starting from the last line
- lastvar (int) the number of the last timestep to be read
- **step** (*int*) the stepping between two timesteps
- **precision** (*str*) precision of the input file, Float32 for single precision, Float64 for double precision

- **extrapot** (*bool*) when set to True, potential extrapolation of the magnetic field outside the fluid domain is also computed
- ratio\_out (*float*) ratio of desired external radius to the CMB radius. This is is only used when extrapot=True
- **nrout** (*int*) number of additional radial grid points to compute the potential extrapolation. This is only used when extrapot=True

```
weakref
```

list of weak references to the object (if defined)

## 9.3.9 Support for B\_cmb\_coeff. TAG and (V|B)\_coeff\_r#. TAG files

This class allows to read the  $B\_coeff\_cmb.TAG$  files. It first read the poloidal potential at the CMB and then transform it to the Gauss coefficients  $q_{\ell m}$  and  $h_{\ell m}$  using the getGauss function.

```
>>> # Reads the files B_coeff_cmb.testa, B_coeff_cmb.testb
>>> # and B_coeff_cmb.testc and stack them in one single time series
>>> cmb = MagicCoeffCmb(tag='test[a-c]')
>>> print(cmb.ell, cmb.glm) # print \ell and g_{\ell m}
>>> print(cmb.glm[:, 1, 0]) # time-series of the axisymmetric dipole
>>> plot(cmb.time, cmb.dglmdt[:, 1, 0]) # Secular variation of the dipole
```

\_\_init\_\_ (tag, ratio\_cmb\_surface=1, scale\_b=1, iplot=True, precision='Float64')
A class to read the B\_coeff\_cmb files

#### **Parameters**

- tag (str) if you specify a pattern, it tries to read the corresponding files
- ratio\_cmb\_surface (*float*) ratio of surface ratio to CMB radius (default is 1)
- scale\_b (*float*) magnetic field unit (default is 1)
- **iplot** (*int*) a logical to toggle the plot (default is True)
- precision (char) single or double precision

#### plot()

Display some results when iplot is set to True

```
class magic.coeff.MagicCoeffR (tag, ratio_cmb_surface=1, scale_b=1, iplot=True, field='B', r=1, precision='Float64')
```

This class allows to read the  $B\_coeff\_r\#.TAG$  and  $V\_coeff\_r\#.TAG$  files. It reads the poloidal and toroidal potentials and reconstruct the time series (or the energy) contained in any given mode.

```
>>> # Reads the files V_coeff_r2.test*
>>> cr = MagicCoeffR(tag='test*', field='V', r=2)
>>> print(cr.ell, cr.wlm) # print \ell and w_{\ell m}
>>> # Time-evolution of the poloidal energy in the (\ell=10, m=10) mode
>>> plot(cr.time, cr.epolLM[:, 10, 10])
```

\_\_init\_\_ (tag, ratio\_cmb\_surface=1, scale\_b=1, iplot=True, field='B', r=1, precision='Float64')

- tag (str) if you specify a pattern, it tries to read the corresponding files
- ratio cmb surface (float) ratio of surface ratio to CMB radius (default is 1)

- scale\_b (float) magnetic field unit (default is 1)
- iplot (bool) a logical to toggle the plot (default is True)
- **field** (*str*) 'B', 'V' or 'T' (magnetic field, velocity field or temperature)
- r (int) an integer to characterise which file we want to plot
- precision (str) single or double precision

magic.coeff.deriv(x, y, axis=0)

This function is a simple second order derivative

#### **Parameters**

- **x** (*numpy.ndarray*) input x-axis
- **y** (*numpy.ndarray*) input array

**Returns** an array that contains the derivatives

Return type numpy.ndarray

magic.coeff.getGauss(alm, blm, ell, m, scale\_b, ratio\_cmb\_surface, rcmb)

Get the Gauss coefficients from the real and imaginary parts of the poloidal potential

#### **Parameters**

- alm (numpy.ndarray) real part of the poloidal potential
- blm (numpy.ndarray) imaginary part of the poloidal potential
- **ell** (*numpy.ndarray*) spherical harmonic degree ell
- **scale\_b** (*float*) magnetic field unit (default is 1)
- ratio\_cmb\_surface (float) ratio of surface ratio to CMB radius (default is 1)
- rcmb (float) radius of the outer boundary

## 9.3.10 Support for B[rp]Spec.TAG

```
class magic.MagicRSpec (tag, field='Br', precision='Float32', avg=False)
```

This class allows to read the rB[r|p]Spec.TAG files. Those files contain the time-evolution of the poloidal/toroidal magnetic energy for all radii and for spherical harmonic degrees from 1 to 6. This is an unformatted fortran file.

```
>>> # Read all the `BrSpec.test*` files in the current working directory and
>>> # stack them.
>>> rsp = MagicRSpec(tag='test*', field='Br')
```

```
__init__ (tag, field='Br', precision='Float32', avg=False)
```

### **Parameters**

- tag (str) if you specify a pattern, it tries to read the corresponding files and stack them.
- **field** (*str*) nature of the radial spectra. Possible choices are 'Bt' or 'Bp'
- **precision** (*str*) single or double precision (default single, i.e. 'Float32')
- avg (bool) when set to True, display time averaged quantities

#### plotAvg()

Plotting function for time-averaged profiles

## 9.3.11 Support for TO outputs

class magic.TOMovie (file=None, iplot=True, cm='RdYlBu\_r', cut=0.8, levels=16, avg=True, precision='Float32')

This class allows to read and display the TO\_mov.TAG generated when l\_TOmovie=.true. is True.

```
>>> # This will allow you to pick up one TO_mov files among the existing ones
>>> t = TOMovie()
```

```
>>> # Read TO_mov.N0m2, time-averaged it and display it with 65 contour levels
>>> t = TOMovie(file='TO_mov.N0m2', avg=True, levels=65, cm='seismic')
```

```
__init__ (file=None, iplot=True, cm='RdYlBu_r', cut=0.8, levels=16, avg=True, precision='Float32')
```

#### **Parameters**

- **file** (*str*) the filename of the TO mov file
- **cmap** (*str*) the name of the color map
- **levels** (*int*) the number of contour levels
- cut (float) adjust the contour extrema to max(abs(data))\*cut
- iplot (bool) a boolean to specify if one wants to plot or not the results
- avg (bool) time average of the different forces
- **precision** (*str*) precision of the input file, Float32 for single precision, Float64 for double precision

### weakref

list of weak references to the object (if defined)

```
plot (cut=0.8, levs=16, avg=True, cmap='RdYlBu_r')
    Plotting function
```

### **Parameters**

- **cut** (*float*) adjust the contour extrema to max(abs(data))\*cut
- **levs** (*int*) number of contour levels
- avg (bool) when set to True, quantities are time-averaged
- cmap (str) name of the colormap

## 9.3.12 Run comparison

```
class magic.CompSims (file='liste', field='ts', ncol=4, cm='RdYlBu_r', dpi=96, normed=True, levels=16, type=None, r=0.9, bw=False, ave=False, cut=1)
```

This class allows to compare an analyse several DNS simultaneously. It is possible to compare time-series or *graphic files*. To set it up, you first need to create a file that contains the list of directories you want to analyse:

```
$ cat inputList
E3e4Eps5e3Q05
E3e4Eps2e3Q07
E3e4Eps2e3Q08
E3e4Eps2e3Q09
```

This list thus contains four directories (one run per directory) that can be further analysed:

```
>>> # Display the time-series of kinetic energy on 2 columns
>>> CompSims(file='inputList', field='ts', ncol=2)
>>> # Display the equatorial cuts of v_r
>>> CompSims(file='inputList', field='vr', type='equat', levels=65, cm='seismic')
>>> # Display the radial cuts of B_r at r=0.8 r_o
>>> CompSims(file='inputList', field='br', type='surf', r=0.8)
>>> # Display the average zonal flow
>>> CompSims(file='inputList', field='vp', type='avg')
```

\_\_init\_\_ (file='liste', field='ts', ncol=4, cm='RdYlBu\_r', dpi=96, normed=True, levels=16, type=None, r=0.9, bw=False, ave=False, cut=1)

#### **Parameters**

- file (str) the input file that contains the list of directories that one wants to analyse
- **field** (*str*) name of the input field. Possible options are: 'ts': displaye the time-series of kinetic energy; 'e\_mag': display the time-series of magnetic energy; 'flux': display the time-series of the Nusselt numbers; 'zonal': display the surface zonal flow; 'Anything else': try to interpret the field
- **type** (*str*) nature of the plot. Possible values are: 'avg' or 'slice': phi-average or phi-slice; 'equat': equatorial cut; 'surf': radial cut; 'ts\*: time series
- ncol (int) number of columns of the figure
- ave (bool) when set to True, it tries to read a time-averaged graphic file
- **r** (*float*) the radius at which you want to display the input data (in normalised units with the radius of the outer boundary)
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- **normed** (*bool*) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.
- **dpi** (*int*) dot per inch when saving PNGs
- **bw** (bool) when set to True, display grey-scaled contour levels
- **cut** (*float*) adjust the contour extrema to max(abs(data))\*cut

## \_\_weakref\_

list of weak references to the object (if defined)

### plotAvg()

Plot azimutal averages in (theta, r) planes.

## plotEmag()

Plot time-series of the magnetic energy

#### plotEquat()

Plot equatorial cuts in (phi, r) planes.

#### plotFlux()

Plot time-series of the top and bottom Nusselt numbers

### plotSurf()

Plot radial cuts in (phi, theta) planes using the Hammer projection.

#### plotTs()

Plot time-series of the kinetic energy

```
plotZonal()
```

Plot surface zonal flow profiles.

## 9.3.13 Additional possible analyses

```
class magic.bLayers.BLayers (iplot=False, quiet=False)
```

This class allows to determine the viscous and thermal boundary layers using several classical methods (slope method, peak values, dissipation rates, etc.). It uses the following files:

- •Kinetic energy: *eKinR.TAG*•Power budget: *powerR.TAG*
- •Radial profiles used for boundary layers: bLayersR.TAG

This function can thus **only** be used when both *powerR.TAG* and *bLayersR.TAG* exist in the working directory.

**Warning:** This function works well as long as rigid boundaries and fixed temperature boundary conditions are employed. Other combination of boundary conditions (fixed fluxes and/or stress-free) might give wrong results, since boundary layers become awkward to define in that case.

Since this function is supposed to use time-averaged quantities, the usual procedure is first to define the initial averaging time using AvqField: (this needs to be done only once)

```
>>> a = AvgField(tstart=2.58)
```

Once the tInitAvg file exists, the boundary layer calculation can be done:

```
>>> bl = BLayers(iplot=True)
>>> # print the formatted output
>>> print(bl)
```

\_\_\_init\_\_\_(iplot=False, quiet=False)

#### **Parameters**

- **iplot** (*bool*) display the result when set to True (default False)
- quiet (bool) less verbose when set to True (default is False)

```
__str__()
```

Formatted output

## plot()

Plotting function

```
magic.bLayers.getAccuratePeaks(rad, uh, uhTop, uhBot, ri, ro)
```

This functions performs a spline extrapolation around the maxima of the input array uh to define a more accurate location of the boundary layer.

- rad (numpy.ndarray) radius
- **uh** (*numpy.ndarray*) the horizontal velocity profile
- **uhTop** (*float*) first peak value of uh close to the outer boundary
- **uhBot** (*float*) first peak value of uh close to the inner boundary
- ri (float) the inner core radius
- ro (float) the outer core radius

**Returns** four floats: thickness of the bottom boundary layer, thickness of the top boundary layer, extrapolated value of uh at the bottom boundary layer, extrapolated value of uh at the top boundary layer

## Return type list

magic.bLayers.getMaxima(field)

This function determines the local maxima of the input array field

**Parameters** field (numpy.ndarray) – the input array

**Returns** a list containing the indices of the local maxima

Return type list

magic.bLayers.integBotTop(rad, field, ri, ro, lambdai, lambdao, normed=False)

This function evaluates the radial integral of the input array field in the bottom and top boundary layers separately.

#### **Parameters**

- rad (numpy.ndarray) radius
- **field** (*numpy.ndarray*) the input radial profile
- ri (float) the inner core radius
- **ro** (*float*) the outer core radius
- lambdai (float) thickness of the inner boundary layer
- lambdao (float) thickness of the outer boundary layer
- **normed** (*bool*) when set to True, the outputs are normalised by the volumes of the boundary layers. In that case, the outputs are volume-averaged quantities.

**Returns** two floats that contains the bottom and top boundary layers integrations (integBot, integTop)

## Return type list

magic.bLayers.integBulkBc(rad, field, ri, ro, lambdai, lambdao, normed=False)

This function evaluates the radial integral of the input array field in the boundary layer and in the bulk separately.

### **Parameters**

- rad (numpy.ndarray) radius
- **field** (*numpy.ndarray*) the input radial profile
- ri (float) the inner core radius
- **ro** (*float*) the outer core radius
- lambdai (float) thickness of the inner boundary layer
- lambdao (float) thickness of the outer boundary layer
- normed (bool) when set to True, the outputs are normalised by the volumes of the boundary layers and the fluid bulk, respectively. In that case, the outputs are volume-averaged quantities.

Returns two floats that contains the boundary layer and the bulk integrations (integBc, integBulk)

Return type list

class magic. ThetaHeat (iplot=False, angle=10, pickleName='thHeat.pickle')

This class allows to conduct some analysis of the latitudinal variation of the heat transfer. It relies on the movie files *ATmov.TAG* and *AHF\_mov.TAG*. As it's a bit time-consuming, the calculations are stored in a python.pickle file to quicken future usage of the data.

This function can **only** be used when *bLayersR.TAG <secBLayersRfile>* exist in the working directory.

Since this function is supposed to use time-averaged quantities, the usual procedure is first to define the initial averaging time using AvgField: (this needs to be done only once)

```
>>> a = AvgField(tstart=2.58)
```

Once the tInitAvq file exists, the latitudinal heat transfer analysis can be done using:

```
>>> # For chunk-averages over 10^\degree in the polar and equatorial regions.
>>> th = ThetaHeat(angle=10)
>>> # Formatted output
>>> print(th)
```

\_\_\_init\_\_\_(iplot=False, angle=10, pickleName='thHeat.pickle')

#### **Parameters**

- **iplot** (*bool*) a boolean to toggle the plots on/off
- angle (*float*) the integration angle in degrees

PickleName calculations a

```
__str__()
Formatted outputs
```

```
>>> th = ThetaHeat()
>>> print(th)
```

plot()

Plotting function

```
class magic.cyl.Cyl(ivar=1, datadir='.', ns=None)
```

This class allows to extrapolate a given *graphic file* on a cylindrical grid. Once done, the extrapolated file is stored in a python.pickle file. It is then possible to display 2-D cuts of the extrapolated arrays (radial cuts, phi-averages, equatorial cuts, z-averages and phi-slices)

**Warning:** This process is actually **very demanding** and it might take a lot of time to extrapolate the G\_#.TAG file. Be careful when choosing the input value of ns!

```
>>> # Extrapolate the G file to the cylindrical grid (ns=128, nz=2*ns)
>>> c = Cyl(ivar=1, ns=128)
>>> # Radial cut of v_r
>>> c.surf(field='vr', r=0.8)
>>> # Vertical average of B_\phi
>>> c.avgz(field='Bphi', cm='seismic', levels=33)
>>> # Azimuthal average of v_\phi
>>> c.avg(field='Bphi')
>>> # Equatorial cut of of v_theta
>>> c.equat(field='vtheta')
```

```
___init___(ivar=1, datadir='.', ns=None)
```

#### **Parameters**

• ivar (int) – the number of the Graphic file

- datadir (str) working directory
- **ns** (*int*) number of grid points in the radial direction

avg (field='Bphi', levels=16, cm='RdYlBu\_r', normed=True, vmax=None, vmin=None) Plot the azimutal average of a given field.

```
>>> c = Cyl(ns=65)
>>> # Azimuthal average of B_r
>>> c.avg(field='Br', cm='seismic', levels=33)
```

#### **Parameters**

- **field** (str) name of the input field
- **levels** (*int*) number of contour levels
- cm (str) name of the color map
- normed (bool) when set to True, the contours are normalised fro -max(field), max(field)
- **vmin** (*float*) truncate the contour levels to values > vmin
- vmax (float) truncate the contour levels to values < vmax

**avgz** (field='vs', levels=16, cm='RdYlBu\_r', normed=True, vmin=None, vmax=None, avg=False) Plot the vertical average of a given field.

```
>>> c = Cyl(ns=65)
>>> # Vertical average of v_s
>>> c.avg(field='vs', cm='seismic', levels=33)
```

#### **Parameters**

- **field** (str) name of the input field
- **levels** (*int*) number of contour levels
- cm (str) name of the color map
- normed (bool) when set to True, the contours are normalised fro -max(field), max(field)
- **vmin** (*float*) truncate the contour levels to values > vmin
- **vmax** (*float*) truncate the contour levels to values < vmax
- **avg** (*bool*) when set to True, an additional figure with the phi-average profile is also displayed

equat (field='vs', levels=16, cm='RdYlBu\_r', normed=True, vmax=None, vmin=None)
Plot an input field in the equatorial plane.

```
>>> c = Cyl(ns=65)
>>> # Equatorial cut of v_\phi
>>> c.equat(field='vphi', cm='seismic', levels=33)
```

- **field** (*str*) name of the input field
- **levels** (*int*) number of contour levels
- cm (str) name of the color map

- normed (bool) when set to True, the contours are normalised fro -max(field), max(field)
- **vmin** (*float*) truncate the contour levels to values > vmin
- vmax (float) truncate the contour levels to values < vmax

**slice** (*field='Bphi'*, *lon\_0=0.0*, *levels=16*, *cm='RdYlBu\_r'*, *normed=True*) Plot an azimuthal slice of a given field.

```
>>> c = Cyl(ns=65)
>>> # Slices of v_r at 30 and 60 degrees
>>> c.slice(field='vr', lon_0=[30, 60])
```

#### **Parameters**

- **field** (str) name of the input field
- 1on 0 (*float or list*) the longitude of the slice in degrees, or a list of longitudes
- **levels** (*int*) number of contour levels
- cm (str) name of the color map
- **normed** (*bool*) when set to True, the contours are normalised fro -max(field), max(field)

surf (field='Bphi', r=0.85, vmin=None, vmax=None, levels=16, cm='RdYlBu\_r', normed=True, figsize=None)

Plot the surface distribution of an input field at a given input radius (normalised by the outer boundary radius).

```
>>> c = Cyl(ns=65)
>>> # Surface plot of B_\phi from -10 to 10
>>> c.surf(field='Bphi', r=0.6, vmin=-10, vmax=10, levels=65)
```

#### **Parameters**

- **field** (*str*) name of the input field
- **r** (*float*) radial level (normalised to the outer boundary radius)
- **levels** (*int*) number of contour levels
- cm (str) name of the color map
- normed (bool) when set to True, the contours are normalised fro -max(field), max(field)
- **vmin** (*float*) truncate the contour levels to values > vmin
- vmax (float) truncate the contour levels to values < vmax

```
magic.cyl.sph2cyl(g, ns=None, nz=None)
```

This function interpolates the three flow (or magnetic field) component of a  $G_{\#}.TAG$  file on a cylindrical grid of size (ns. nz).

Warning: This might be really slow!

- g (magic.MagicGraph) input graphic output file
- **ns** (*int*) number of grid points in the radial direction
- **nz** (*int*) number of grid points in the vertical direction

**Returns** a python tuple of five numpy.ndarray (S,Z,vs,vp\_cyl,vz). S[nz,ns] is a meshgrid that contains the radial coordinate. Z[nz,ns] is a meshgrid that contains the vertical coordinate. vs[nz,ns] is the radial component of the velocity (or magnetic field), vp\_cyl[nz,ns] the azimuthal component and vz[nz,ns] the vertical component.

## Return type tuple

magic.cyl.sph2cyl\_plane(data, rad, ns, nz)

This function extrapolates a phi-slice of a spherical shell on a cylindrical grid

```
>>> # Read G_1.test
>>> gr = MagicGraph(ivar=1, tag='test')
>>> # phi-average v_\phi and s
>>> vpm = gr.vphi.mean(axis=0)
>>> sm = gr.entropy.mean(axis=0)
>>> # Interpolate on a cylindrical grid
>>> S, Z, outputs = sph2cyl_plane([vpm, sm], gr.radius, 512, 1024)
>>> vpm_cyl, sm_cyl = outputs
```

#### **Parameters**

- data (list(numpy.ndarray)) a list of 2-D arrays [(ntheta, nr), (ntheta, nr), ...]
- rad (numpy.ndarray) radius
- **ns** (*int*) number of grid points in s direction
- **nz** (*int*) number of grid points in z direction

**Returns** a python tuple that contains two numpy.ndarray and a list (S,Z,output). S[nz,ns] is a meshgrid that contains the radial coordinate. Z[nz,ns] is a meshgrid that contains the vertical coordinate. output=[arr1[nz,ns], ..., arrN[nz,ns]] is a list of the interpolated array on the cylindrical grid.

## Return type tuple

magic.cyl.zavg(input, radius, ns, minc, save=True, filename='vp.pickle', normed=True)

This function computes a z-integration of a list of input arrays (on the spherical grid). This works well for 2-D (phi-slice) arrays. In case of 3-D arrays, only one element is allowed (too demanding otherwise).

### **Parameters**

- input (*list(numpy.ndarray*)) a list of 2-D or 3-D arrays
- radius (numpy.ndarray) spherical radius
- **ns** (*int*) radial resolution of the cylindrical grid (nz=2\*ns)
- minc (int) azimuthal symmetry
- **save** (*bool*) a boolean to specify if one wants to save the outputs into a pickle (default is True)
- **filename** (*str*) name of the output pickle when save=True
- **normed** (*bool*) a boolean to specify if ones wants to simply integrate over z or compute a z-average (default is True: average)

**Returns** a python tuple that contains two numpy.ndarray and a list (height,cylRad,output) height[ns] is the height of the spherical shell for all radii. cylRad[ns] is the cylindrical radius. output=[arr1[ns], ..., arrN[ns]] contains the z-integrated output arrays.

## Return type tuple

```
 \begin{array}{c} \textbf{class} \ \texttt{magic.Butterfly} \ (\textit{file=None}, \ \textit{step=1}, \ \textit{iplot=True}, \ \textit{rad=0.8}, \ \textit{lastvar=None}, \ \textit{nvar='all'}, \ \textit{levels=20}, \\ \textit{cm='RdYlBu_r'}, \textit{precision='Float32'}, \textit{cut=0.8}) \end{array}
```

This class can be used to display the time evolution of the magnetic field for various latitudes (i.e. the well-known butterfly diagrams). These diagrams are usually constructed using MagIC's *movie files*: either radial cuts (like Br\_CMB\_mov.TAG) or azimuthal-average (like AB\_mov.TAG).

## \_\_\_add\_\_\_(new)

Overload of the addition operator

```
>>> # Read 2 files
>>> b1 = Butterfly(file='AB_mov.test1', iplot=False)
>>> b2 = Butterfly(file='AB_mov.test2', iplot=False)
>>> # Stack them and display the whole thing
>>> b = b1+b2
>>> b.plot(levels=33, contour=True, cut=0.8, cm='seismic')
```

```
__init__ (file=None, step=1, iplot=True, rad=0.8, lastvar=None, nvar='all', levels=20, cm='RdYlBu_r', precision='Float32', cut=0.8)
```

#### **Parameters**

- **file** (*str*) when specified, the constructor reads this file, otherwise a list with the possible options is displayed
- rad (*float*) radial level (normalised to the outer boundary radius)
- **iplot** (*bool*) display/hide the plots (default is True)
- **nvar** (*int*) the number of time steps (lines) of the movie file we want to plot starting from the last line
- lastvar (int) the number of the last time step to be read
- **step** (*int*) the stepping between two lines
- levels (int) the number of contour levels
- cm (str) the name of the color map
- cut (float) adjust the contour extrema to max(abs(data))\*cut
- **precision** (*bool*) precision of the input file, Float32 for single precision, Float64 for double precision

## \_\_weakref\_

list of weak references to the object (if defined)

#### fourier2D (renorm=False)

This function allows to conduct some basic Fourier analysis on the data. It displays two figures: the first one is a contour levels in the (Frequency, Latitude) plane, the second one is integrated over latitudes (thus a simple, power vs Frequency plot)

```
>>> # Load the data without plotting
>>> b1 = Butterfly(file='AB_mov.test1', iplot=False)
>>> # Fourier analysis
>>> b1.fourier2D()
```

**Parameters renorm** (*bool*) – when set to True, it rebins the time series in case of irregularly spaced data

plot (levels=12, contour=False, renorm=False, cut=0.5, mesh=3, cm='RdYlBu\_R')
 Plotting function

#### **Parameters**

- **cm** (*str*) name of the colormap
- **levels** (*int*) the number of contour levels (only used when iplot=True and contour=True)
- **contour** (*bool*) when set to True, display contour levels (pylab.contourf), when set to False, display an image (pylab.imshow)
- renorm (bool) when set to True, it re-bins the time series in case of irregularly time-spaced data
- mesh (int) when renorm=True, factor of regriding: NewTime = mesh\*OldTime
- cut (float) adjust the contour extrema to max(abs(data))\*cut

## 9.3.14 Various useful functions

magic.libmagic.anelprof (radius, strat, polind, g0=0.0, g1=0.0, g2=1.0)

This functions calculates the reference temperature and density profiles of an anelastic model.

```
>>> rad = chebgrid(65, 1.5, 2.5)
>>> temp, rho, beta = anelprof(rad, strat=5., polind=2.)
```

#### **Parameters**

- radius (numpy.ndarray) the radial gridpoints
- **polind** (*float*) the polytropic index
- **strat** (*float*) the number of the density scale heights between the inner and the outer boundary
- **g0** (*float*) gravity profile: g=g0
- **g1** (*float*) gravity profile: g=g1\*r/r\_o
- q2 (float) gravity profile: g=g2\*(r o/r)\*\*2

**Returns** a tuple that contains the temperature profile, the density profile and the log-derivative of the density profile versus radius

Return type (numpy.ndarray, numpy.ndarray, numpy.ndarray)

 $\verb|magic.libmagic.avgField| (\textit{time}, \textit{field}, \textit{tstart})$ 

This subroutine computes the time-average of a time series

```
>>> ts = MagicTs(field='misc', iplot=False, all=True)
>>> nuavg = avgField(ts.time, ts.topnuss, 0.35)
>>> print(nuavg)
```

#### **Parameters**

• time (numpy.ndarray) - time

- **field** (*numpy.ndarray*) the time series of a given field
- **tstart** (*float*) the starting time of the averaging

Returns the time-averaged quantity

Return type float

magic.libmagic.chebgrid(nr, a, b)

This function defines a Gauss-Lobatto grid from a to b.

```
>>> r_icb = 0.5 ; r_cmb = 1.5; n_r_max=65
>>> rr = chebgrid(n_r_max, r_icb, r_cmb)
```

## **Parameters**

- **nr** (*int*) number of radial grid points
- a (float) lower limit of the Gauss-Lobatto grid
- **b** (*float*) upper limit of the Gauss-Lobatto grid

Returns the Gauss-Lobatto grid

Return type numpy.ndarray

```
magic.libmagic.cut (dat, vmax=None, vmin=None)
```

This functions truncates the values of an input array that are beyond vmax or below vmin and replace them by vmax and vmin, respectively.

```
>>> # Keep only values between -1e3 and 1e3
>>> datNew = cut(dat, vmin=-1e3, vmax=1e3)
```

### **Parameters**

- dat (numpy.ndarray) an input array
- vmax (float) maximum upper bound
- vmin (float) minimum lower bound

**Returns** an array where the values >=vmax have been replaced by vmax and the values <=vmin have been replaced by vmin

Return type numpy.ndarray

```
magic.libmagic.cylSder(radius, data)
```

This function computes the s derivative of an input array defined on a regularly-spaced cylindrical grid.

```
>>> s = linspace(0., 1., 129; dat = cos(s)
>>> ddatds = cylSder(s, dat)
```

### **Parameters**

- radius (numpy.ndarray) cylindrical radius
- data (numpy.ndarray) input data

**Returns** s derivative

Return type numpy.ndarray

```
magic.libmagic.cylZder(z, data)
```

This function computes the z derivative of an input array defined on a regularly-spaced cylindrical grid.

```
>>> z = linspace(-1., 1., 129 ; dat = cos(z)
>>> ddatdz = cylZder(z, dat)
```

#### **Parameters**

- **z** (*numpy.ndarray*) height of the cylinder
- data (numpy.ndarray) input data

**Returns** z derivative

Return type numpy.ndarray

```
\verb|magic.libmagic.fast_read| (\textit{file}, \textit{skiplines} = 0, \textit{binary} = \textit{False}, \textit{precision} = \textit{`Float64'})|
```

This function reads an input ascii table (can read both formatted or unformatted fortran)

```
>>> # Read 'e_kin.test', skip the first 10 lines
>>> data = fast_read('e_kin.test', skiplines=10)
```

#### **Parameters**

- **file** (*str*) name of the input file
- **skiplines** (*int*) number of header lines to be skept during reading
- **binary** (*bool*) when set to True, try to read an unformatted binray Fortran file (default is False)
- **precision** (*str*) single ('Float32') or double precision ('Float64')

Returns an array[nlines, ncols] that contains the data of the ascii file

Return type numpy.ndarray

```
magic.libmagic.getCpuTime (file)
```

This function calculates the CPU time from one given log file

**Parameters file** (*file*) – the log file you want to analyze

Returns the total CPU time

Return type float

```
magic.libmagic.getTotalRunTime()
```

This function calculates the total CPU time of one run directory

Returns the total RUN time

Return type float

magic.libmagic.hammer2cart (ttheta, pphi, colat=False)

This function is used to define the Hammer projection used when plotting surface contours in magic. Surf

```
>>> # Load Graphic file
>>> gr = MagicGraph()
>>> # Meshgrid
>>> pphi, ttheta = mgrid[-N.pi:N.pi:gr.nphi*1j, N.pi/2.:-N.pi/2.:gr.ntheta*1j]
>>> x,y = hammer2cart(ttheta, pphi)
>>> # Contour plots
>>> contourf(x, y, gr.vphi)
```

#### **Parameters**

- ttheta (numpy.ndarray) meshgrid [nphi, ntheta] for the latitudinal direction
- **pphi** meshgrid [nphi, ntheta] for the azimuthal direction
- colat (numpy.ndarray) colatitudes (when not specified a regular grid is assumed)

**Returns** a tuple that contains two [nphi, ntheta] arrays: the x, y meshgrid used in contour plots

**Return type** (numpy.ndarray, numpy.ndarray)

```
magic.libmagic.intcheb (f, nr, z1, z2)
```

This function integrates an input function f defined on the Gauss-Lobatto grid.

```
>>> print(intcheb(f, 65, 0.5, 1.5))
```

#### **Parameters**

- f an input array
- **nr** (*int*) number of radial grid points
- **z1** (*float*) lower limit of the Gauss-Lobatto grid
- **z2** (*float*) upper limit of the Gauss-Lobatto grid

Type numpy.ndarray

Returns the integrated quantity

Return type float

```
magic.libmagic.matder (nr, z1, z2)
```

This function calculates the derivative in Chebyshev space.

```
>>> r_icb = 0.5; r_cmb = 1.5; n_r_max=65
>>> d1 = matder(n_r_max, r_icb, r_cmb)
>>> # Chebyshev grid and data
>>> rr = chebgrid(n_r_max, r_icb, r_cmb)
>>> f = sin(rr)
>>> # Radial derivative
>>> df = dot(d1, f)
```

### **Parameters**

- **nr** (*int*) number of radial grid points
- **z1** (*float*) lower limit of the Gauss-Lobatto grid
- **z2** (*float*) upper limit of the Gauss-Lobatto grid

Returns a matrix of dimension (nr,nr) to calculate the derivatives

**Return type** numpy.ndarray

```
magic.libmagic.phideravg(data, minc=1) phi-derivative of an input array
```

```
pin-derivative of an input array
```

```
>>> gr = MagicGraph()
>>> dvphidp = phideravg(gr.vphi, minc=gr.minc)
```

- data (*numpy.ndarray*) input array
- minc (int) azimuthal symmetry

Returns the phi-derivative of the input array

Return type numpy.ndarray

```
magic.libmagic.progressbar(it, prefix='', size=60)
```

Fancy progress-bar for loops

```
for i in progressbar(range(1000000)):

x = i
```

#### **Parameters**

- **prefix** (*str*) prefix string before progress bar
- **size** (*int*) width of the progress bar (in points of xterm width)

magic.libmagic.rderavg(data, eta=0.35, spectral=True, exclude=False)

Radial derivative of an input array

```
>>> gr = MagiGraph()
>>> dvrdr = rderavg(gr.vr, eta=gr.radratio)
```

#### **Parameters**

- data (numpy.ndarray) input array
- eta (float) aspect ratio of the spherical shell
- **spectral** (*bool*) when set to True use Chebyshev derivatives, otherwise use finite differences (default is True)
- **exclude** (*bool*) when set to True, exclude the first and last radial grid points and replace them by a spline extrapolation (default is False)

**Returns** the radial derivative of the input array

**Return type** numpy.ndarray

```
magic.libmagic.scanDir(pattern, tfix=None)
```

This function sorts the files which match a given input pattern from the oldest to the most recent one (in the current working directory)

```
>>> dat = scanDir('log.*')
>>> print(log)
```

#### **Parameters**

- pattern (str) a classical regexp pattern
- **tfix** (*float*) in case you want to add only the files that are more recent than a certain date, use tfix (computer 1970 format!!)

**Returns** a list of files that match the input pattern

Return type list

```
magic.libmagic.sderavg(data, eta=0.35, spectral=True, colat=None, exclude=False) s derivative of an input array
```

```
>>> gr = MagiGraph()
>>> dvpds = sderavg(gr.vphi, eta=gr.radratio, colat=gr.colatitude)
```

#### **Parameters**

- data (numpy.ndarray) input array
- eta (float) aspect ratio of the spherical shell
- **spectral** (*bool*) when set to True use Chebyshev derivatives, otherwise use finite differences (default is True)
- **exclude** (*bool*) when set to True, exclude the first and last radial grid points and replace them by a spline extrapolation (default is False)
- colat (numpy.ndarray) colatitudes (when not specified a regular grid is assumed)

**Returns** the s derivative of the input array

Return type numpy.ndarray

```
magic.libmagic.selectField(obj, field, labTex=True)
```

This function selects for you which field you want to display. It actually allows to avoid possible variables miss-spelling: i.e. 'Bphi'='bp'='Bp'='bphi'

#### **Parameters**

- obj (magic.MagicGraph) a graphic output file
- **field** (*str*) the name of the field one wants to select
- labTex (bool) when set to True, format the labels using LaTeX fonts

**Returns** a tuple that contains the selected physical field and its label

**Return type** (numpy.ndarray, str)

```
magic.libmagic.symmetrize(data, ms)
```

Symmetrise an array which is defined only with an azimuthal symmetry minc=ms

#### **Parameters**

- data (numpy.ndarray) the input array
- **ms** (*int*) the azimuthal symmetry

**Returns** an output array of dimension (data.shape[0]\*ms+1)

Return type numpy.ndarray

```
magic.libmagic.thetaderavg(data, order=4)
```

Theta-derivative of an input array (finite differences)

```
>>> gr = MagiGraph()
>>> dvtdt = thetaderavg(gr.vtheta)
```

## **Parameters**

- data (*numpy.ndarray*) input array
- order (int) order of the finite-difference scheme (possible values are 2 or 4)

**Returns** the theta-derivative of the input array

Return type numpy.ndarray

magic.libmagic.writeVpEq(par, tstart)

This function computes the time-averaged surface zonal flow (and Rolc) and format the output

```
>>> # Reads all the par.* files from the current directory
>>> par = MagicTs(field='par', iplot=False, all=True)
>>> # Time-average
>>> st = writeVpEq(par, tstart=2.1)
>>> print(st)
```

## **Parameters**

- par (magic.MagicTs) a MagicTs object containing the par file
- **tstart** (*float*) the starting time of the averaging

**Returns** a formatted string

Return type str

magic.libmagic.zderavg (data, eta=0.35, spectral=True, colat=None, exclude=False) z derivative of an input array

```
>>> gr = MagiGraph()
>>> dvrdz = zderavg(gr.vr, eta=gr.radratio, colat=gr.colatitude)
```

#### **Parameters**

- data (numpy.ndarray) input array
- eta (float) aspect ratio of the spherical shell
- **spectral** (*bool*) when set to True use Chebyshev derivatives, otherwise use finite differences (default is True)
- **exclude** (*bool*) when set to True, exclude the first and last radial grid points and replace them by a spline extrapolation (default is False)
- colat (numpy.ndarray) colatitudes (when not specified a regular grid is assumed)

**Returns** the z derivative of the input array

Return type numpy.ndarray

**CHAPTER** 

**TEN** 

## **DESCRIPTION OF THE FORTRAN MODULES**

The following pages contain an exhaustive description of the different variables, subroutines and modules used in MagIC. This documentation is automatically generated from the source code docstrings using the Sphinx extention for the Fortran domain.

#### Fortran modules

- 1. For the main program file magic.f90, see *here*.
- 2. For the core modules that contain most of the global variables, see *here*.
- 3. For the MPI related modules, see *here*.
- 4. For the code initialization and the pre-calculations done in the initial stage of the computation (before the time-stepping loop), see *here* and *there*.
- 5. For the time-stepping loop, see *here*.
- 6. For the calculation of the non-linear terms (in the physical space) and their time-advance, see *here*.
- 7. For the calculation of the linear terms (in spectral space) and their time-advance, see *here*.
- 8. For the Chebyshev, Fourier and Legendre transforms, see *here*.
- 9. For the computation of the radial derivatives (Chebyshev) and the integration, see *here*.
- 10. For the definition of the blocking, see *here*.
- 11. For the calculation of the standard outputs (time-series, spectra and radial files), see *here*.
- 12. For the calculation of binary outputs (graphic files, movie files, potential and coeff files), see here.
- 13. For the additional calculations of specific outputs (torsional oscillations, RMS force balance, etc.), see *here*.
- 14. For reading and writing the check points (restart files), see *here*.
- 15. For additional useful functions (string manipulation, HDF5 support, etc.), see here.

# 10.1 Main program magic.f90

## program magic

A dynamic dynamo model driven by thermal convection in a rotating spherical fluid shell. This version can solve for both Boussinesq and anelastic fluids and non-dimensional variables are used throughout the whole code.

```
Use physical_parameters,
                            init fields,
                                             output data,
   (codeversion()), start_fields (getstartfields()), blocking, fields,
                 (initialize movie data(),
                                               finalize movie data()),
   movie data
   truncation,
                  spectra
                              (initialize spectra()),
                                                         parallel mod,
   magnetic energy,
                          step time mod
                                              (initialize step time(),
                            (initialize_output_power()),
   step_time()),
                   power
                                                             egeos_mod,
   output_mod
                      (initialize_output()),
                                                        communications
   (initialize_communications()),
                                                    namelists,
                                      matrices,
```

```
(initialize_rms()), timing (walltime(), writetime()), outpar_mod (initialize_outpar_mod()), lmloop_mod (initialize_lmloop()), precision_mod, radialloop, kinetic_energy, horizontal_data, logic, radial_functions, outpv3 (initialize_outpv3()), fields_average_mod, radial_data (initialize_radial_data()), torsional_oscillations, outto_mod (initialize_outto_mod()), dtb_mod (initialize_dtb_mod()), grenoble, precalculations, fieldslast, num_param, lmloop_data (initialize_lmloop_data())
```

```
Call to parallel(),
                 walltime(), writetime(), readnamelists(),
  openfiles(),
  initialize_blocking(),
                                      initialize_radial_data(),
  initialize_radial_functions(),
                                      initialize_radialloop(),
  initialize_lmloop_data(),
                                            initialize_lmloop(),
  initialize_num_param(), initialize_to(), initialize_outto_mod(),
  initialize_init_fields(),
                                         initialize_grenoble(),
  initialize_horizontal_data(),
                                         initialize_matrices(),
  initialize_fields(), initialize_fieldslast(), initialize_rms(),
  initialize dtb mod(),
                                   initialize kinetic energy(),
  initialize_magnetic_energy(), initialize_fields_average_mod(),
  initialize_egeos_mod(), initialize_spectra(), initialize_outpv3(),
  initialize_step_time(),
                                    initialize_communications(),
  initialize_outpar_mod(), initialize_output_power(), precalc(),
  initialize movie data(),
                          writenamelists(), getstartfields(),
  precalctimes(), writeinfo(), step_time(), finalize_movie_data(),
  closefiles()
```

## 10.2 Base modules

## **10.2.1** precision.f90

#### Description

This module controls the precision used in MagIC

#### **Quick access**

```
Variables sizeof_def_complex, sizeof_def_real, sizeof_out_real, lip, sizeof_integer, mpi_out_real, mpi_def_complex, cp, mpi_def_real, sizeof_character,outp
```

## **Needed modules**

• mpi

### **Variables**

- precision\_mod/sizeof\_def\_complex [integer,parameter=16/public]
- precision\_mod/mpi\_def\_real [integer,parameter=mpi\_real8/public]

- precision\_mod/lip[integer,parameter=selected\_int\_kind(12)/public]
- precision\_mod/sizeof\_def\_real [integer,parameter=8/public]
- precision\_mod/mpi\_out\_real [integer,parameter=mpi\_real4/public]
- precision\_mod/sizeof\_character[integer,parameter=1/public]
- precision\_mod/mpi\_def\_complex [integer,parameter=mpi\_complex 16/public]
- precision mod/cp [integer, parameter=selected real kind(15)/public]
- precision\_mod/outp [integer,parameter=selected\_real\_kind(6)/public]
- precision\_mod/sizeof\_out\_real [integer,parameter=4/public]
- precision\_mod/sizeof\_integer[integer,parameter=4/public]

# 10.2.2 truncation.f90

## **Description**

This module defines the grid points and the truncation

#### **Quick access**

Variables nalias, lstressmem, n\_cheb\_ic\_max, lavemem, n\_r\_max, n\_r\_max\_dtb, lm\_max, lm\_max\_dtb, n\_r\_maxmag, lm\_maxmag, nrp, lm\_max\_real, n\_phi\_maxstr, n\_r\_tot, lmp\_max, l\_maxmag, ncpgeos, n\_cheb\_max, n\_r\_max\_ave, lm\_maxgeos, ldtbmem, n\_phi\_max, l\_max, lmp\_max\_dtb, n\_theta\_max, ncp, n\_r\_ic\_maxmag, n\_r\_ic\_max\_dtb, nrpgeos, n\_theta\_maxstr, n\_r\_maxgeos, minc, n\_phi\_tot, lm\_max\_ave, lgeos, n\_r\_totmag, lmoviemem, n\_m\_max, n\_r\_ic\_max\_ave, n\_r\_maxstr, lmagmem, n\_r\_ic\_max, m\_max

**Routines** checktruncation(), initialize\_truncation()

## **Variables**

- truncation/n\_r\_max [integer] number of radial grid points
- truncation/lm\_max\_real [integer]
  number of l/m combination for real representation (cos/sin)
- truncation/**lmagmem** [integer]

  Memory for magnetic field calculation
- truncation/ncp [integer]
- truncation/**nrp** [integer] dimension of phi points in for real/complex arrays
- truncation/n\_phi\_max [integer]
   absolute number of phi grid-points
- truncation/lgeos [integer]

  Memory for Geostrophic output

- truncation/n\_r\_maxstr [integer]

  Number of radial points for stress output
- truncation/nrpgeos [integer]
   Number of cyl. radial points for Geostrophic output
- truncation/n\_phi\_tot [integer] number of longitude grid points
- truncation/n\_r\_ic\_max [integer]
   number of grid points in inner core
- truncation/lm\_max\_dtb [integer]

  Number of l/m combinations for movie output
- truncation/m\_max [integer]
  max order of Plms
- truncation/n\_r\_ic\_maxmag [integer]

  Number of radial points to calculate IC magnetic field
- truncation/n\_theta\_maxstr[integer]

  Number of theta points for stress output
- truncation/lm\_maxgeos [integer]
   Number of I/m combinations for Geostrophic output
- truncation/n\_r\_totmag[integer] n\_r\_maxMag + n\_r\_ic\_maxMag
- truncation/lmp\_max[integer]
  number of l/m combination if l runs to l\_max+1
- truncation/lstressmem[integer]

  Memory for stress output
- truncation/n\_r\_maxgeos [integer]

  Number of radial points for Geostrophic output
- truncation/**1\_max** [integer] max degree of Plms
- truncation/n\_r\_maxmag [integer]

  Number of radial points to calculate magnetic field
- truncation/n\_r\_max\_dtb [integer]

  Number of radial points for movie output
- truncation/**lmoviemem** [integer]

  Memory for movies
- truncation/n\_phi\_maxstr [integer]

  Number of phi points for stress output
- truncation/n\_m\_max [integer]
  max number of ms (different oders)
- truncation/1\_maxmag [integer]
   Max. degree for magnetic field calculation
- truncation/lm\_maxmag [integer]

  Max. number of l/m combinations for magnetic field calculation

- truncation/n\_cheb\_max [integer] max degree-1 of cheb polynomia
- truncation/lavemem[integer]

  Memory for calculating time averages
- truncation/nalias [integer] controls dealiasing in latitude and
- truncation/n\_cheb\_ic\_max[integer] number of chebs in inner core
- truncation/ldtbmem[integer]

  Memory for movie output
- truncation/n\_r\_max\_ave [integer]

  Number of radial points for time average
- truncation/n\_theta\_max [integer] number of theta grid-points
- truncation/ncpgeos[integer]
- truncation/n\_r\_tot [integer]
   total number of radial grid points
- truncation/lmp\_max\_dtb [integer]

  Number of l/m combinations for movie output if l runs to l\_max+1
- truncation/lm\_max [integer]
  number of l/m combinations
- truncation/n\_r\_ic\_max\_ave [integer]

  Number of IC radial points for time average
- truncation/minc[integer]
  basic wavenumber, longitude symmetry
- truncation/lm\_max\_ave [integer]

  Number of l/m combinations for time average
- truncation/n\_r\_ic\_max\_dtb [integer]
   Number of IC radial points for movie output

```
{\bf subroutine} \; {\tt truncation/initialize\_truncation} \; () \\
```

Called from readnamelists()

#### subroutine truncation/checktruncation()

This function checks truncations and writes it into STDOUT and the log-file. MPI: called only by the processor responsible for output!

Called from magic

## 10.2.3 num param.f90

## **Description**

Module containing numerical and control parameters

#### **Quick access**

Variables delxh2, delxr2, runtimestart, runtime, runtimelimit, dtmin, difkap, alpha, enscale, escale, pscale, courfac, vscale, amstart, tscale, lscale, intfac, difnu, timestart, dtmax, alffac, tend, dtstart, difeta, n\_time\_steps, n\_cour\_step, istop, n\_tscale, n\_lscale, ldifexp, ldif

Routines initialize\_num\_param()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- truncation (n\_r\_max()): This module defines the grid points and the truncation

#### **Variables**

- num\_param/amstart [real,public]
- num\_param/intfac [real,public]

  Value to re-scale dtMax during simulation
- num\_param/dtmax [real,public]

  Maximum allowed time step
- num\_param/dtstart [real,public]
   Initial time step if start solution is initialized
- num\_param/n\_lscale [integer,public]
  Control length scale
- num\_param/timestart [real,public]
   Numerical time where run should start
- num\_param/n\_tscale[integer,public]
  Control time scale
- num\_param/runtimestart (4) [integer,public]
   Wall clock time of start of the run
- num\_param/alpha [real,public]
  Weight for implicit time step
- num\_param/difkap [real,public]
  Amplitude of thermal hyperdiffusion
- num\_param/n\_cour\_step [integer,public]
  Step for controlling Courant criteria
- num\_param/runtime (4) [integer,public]
  Running time

- num\_param/difeta [real,public]
  Amplitude of magnetic hyperdiffusion
- num\_param/escale [real,public]
  Energy scale
- num\_param/vscale [real,public]
  Velocity scale
- num\_param/ldif [integer,public]

  Degree where hyperdiffusion starts to act
- num\_param/enscale [real,public]
  Energies scale
- num\_param/alffac [real,public]
   Value to scale Alfen-velocity in courant criteria
- num\_param/dtmin [real,public]

  Minimum allowed time step
- num\_param/ldifexp[integer,public]
   Exponent for hyperdiffusion function
- num\_param/n\_time\_steps [integer,public]

  Total number of time steps requested in the name list
- num\_param/delxh2 (:) [real,allocatable/public]
- num\_param/pscale [real,public]
- num\_param/lscale [real,public]
  Length scale
- num\_param/runtimelimit (4) [integer,public]

  Maximum running time
- num\_param/courfac [real,public]

  Value to scale velocity in courant criteria
- num\_param/istop[integer,public]
  Variable used in FFT soubroutine
- num\_param/difnu [real,public]
  Amplitude of viscous hyperdiffusion
- num\_param/tend [real,public]
   Numerical time where run should end
- num\_param/tscale [real,public]
  Time scale
- num\_param/delxr2 (:) [real,allocatable/public]

```
subroutine num_param/initialize_num_param()
Called from magic
```

# 10.2.4 phys\_param.f90

## **Description**

Module containing the physical parameters

#### **Quick access**

Variables n\_imps\_max, thetas, peaks, widths, phis, interior\_model, cmbhflux, con\_lambdaout, buofac, slopestrat, r\_cut\_model, con\_radratio, ekscaled, pr, o\_sr, ra, ohmlossfac, tmagcon, g2, opm, rascaled, prmag, r\_lcr, vischeatfac, con\_lambdamatch, lffac, sigma\_ratio, conductance\_ma, g1, epss, radratio, opr, con\_funcwidth, corfac, polind, rho\_ratio\_ma, strat, g0, epsc, ek, epsc0, dissnb, difexp, rho\_ratio\_ic, con\_decrate, kbots, ktopb, ktops, ktopv, mode, kbotv, n\_r\_lcr, nvareps, imps, nvardiff, imagcon, n\_imps, nvarvisc, nvarcond, kbotb

#### **Needed modules**

• precision\_mod: This module controls the precision used in MagIC

#### **Variables**

- physical\_parameters/**phis** (20) [real]
- physical\_parameters/o\_sr [real]
   Inverse of sigma\_ratio
- physical\_parameters/**epss** [real]

  Deviation from the adiabat
- physical\_parameters/widths (20) [real]
- physical\_parameters/**r\_lcr** [real]

  Radius beyond which conductivity is zero
- physical\_parameters/conductance\_ma [real]
   OC conductivity
- physical\_parameters/ra[real]
   Rayleigh number
- physical\_parameters/**strat** [real] number of density scale heights
- physical\_parameters/slopestrat [real] stratified Layer
- physical\_parameters/**dissnb** [real]
  Dissipation number
- physical\_parameters/**difexp** [real]
  Thermal diffusivity variation
- physical\_parameters/mode [integer]
   Mode of calculation

- physical\_parameters/rho\_ratio\_ma [real]
  Same density as outer core
- physical\_parameters/**ekscaled** [real] Ekman\*lscale\*\*2
- physical\_parameters/thetas(20)[real]
- physical\_parameters/rho\_ratio\_ic [real]
  Same density as outer core
- physical\_parameters/n\_imps [integer]
   Heat boundary condition
- physical\_parameters/con\_funcwidth [real]
   nVarCond=1
- physical\_parameters/**g2** [real] Set to 1.0 for 1/r\*\*2 gravity
- physical\_parameters/interior\_model [character]
   name of the interior model
- physical\_parameters/**epsc0** [real]
  Internal heat source magnitude
- physical\_parameters/**g0** [real] Set to 1.0 for constant gravity
- physical\_parameters/kbotv [integer]
- physical\_parameters/**sigma\_ratio** [real] Value of IC rotation
- physical\_parameters/ek [real]
   Ekman number
- physical\_parameters/**r\_cut\_model** [real]

  Percentage on the inner part of the interior model to be used
- physical\_parameters/epsc[real]
  Renormalisation of epsc0
- physical\_parameters/nvareps [integer]
  Selection of internal heating profile
- physical\_parameters/cmbhflux [real] stratified Layer
- physical\_parameters/rascaled[real]
  Ra\*Iscale\*\*3
- physical\_parameters/polind [real] polytropic index
- physical\_parameters/kbotb[integer]
- physical\_parameters/ktopv [integer]
   Velocity boundary condition
- physical\_parameters/ohmlossfac[real]
  Dissipation number ViscHeatFac/(ekScaled\*prmag\*\*2)
- physical\_parameters/corfac[real]
  Inverse of ekScaled

- physical\_parameters/radratio [real] aspect ratio
- physical\_parameters/**pr**[real]

  Prandtl number
- physical\_parameters/con\_decrate [real]
  Slope of electrical conductivity profile (nVarCond=2)
- physical\_parameters/peaks (20) [real]
- physical\_parameters/nvarvisc[integer]
  Selection of variable viscosity profile
- physical\_parameters/con\_lambdamatch [real]
  Electrical conductivity at con\_RadRatio (nVarCond=2)
- physical\_parameters/prmag[real] magnetic Prandtl number
- physical\_parameters/nvardiff [integer]
   Selection of variable diffusivity profile
- physical\_parameters/con\_lambdaout [real]
   nVarCond=1
- physical\_parameters/imps [integer]
   Heat boundary condition
- physical\_parameters/tmagcon [real]
  Time for magnetoconvection calculation
- physical\_parameters/ktopb [integer]
   Magnetic boundary condition
- physical\_parameters/nvarcond [integer]
   Selection of variable conductivity profile
- physical\_parameters/kbots[integer]
- physical\_parameters/**vischeatfac** [real]
  Dissipation number \*Pr/raScaled
- physical\_parameters/**opm** [real]
  Inverse of magnetic Prandtl number
- physical\_parameters/imagcon [integer]
  Imposed magnetic field for magnetoconvection, at the boundaries
- physical\_parameters/ktops [integer]
  Entropy boundary condition
- physical\_parameters/n\_r\_lcr [integer]
   Number of radial points where conductivity is zero
- physical\_parameters/**g1** [real] Set to 1.0 for linear gravity
- physical\_parameters/buofac [real]
  Ratio of Rayleigh number over Prandtl number
- physical\_parameters/n\_imps\_max [integer,parameter=20]
  Heat boundary condition

- physical\_parameters/opr[real]
  - Inverse of Prandtl number
- physical\_parameters/lffac[real]

Inverse of Pr\*Ekman

• physical\_parameters/con\_radratio [real]

Transition between branches of electrical conductivity profile (nVarCond=1,2)

# 10.2.5 logic.f90

## **Description**

Module containing the logicals that control the run

#### **Quick access**

Variables lverbose, l\_corrmov, l\_to, l\_cond\_ic, l\_correct\_amz, l\_storepot, l\_storebpot, l\_htmovie, l\_heat, l\_srma, l\_update\_v, l\_b\_nl\_icb, l\_movie, l\_b\_nl\_cmb, l\_rms, l\_store\_frame, l\_fluxprofs, l\_drift, l\_dt\_cmb\_field, l\_dtb, l\_anel, l\_isothermal, l\_true\_time, l\_ht, l\_dtrmagspec, l\_storetpot, l\_power, l\_conv, l\_mag\_kin, l\_tomovie, l\_pv, l\_anelastic\_liquid, l\_mag\_lf, l\_runtimelimit, l\_iner, l\_time\_hits, l\_r\_field, l\_mag\_nl, l\_viscbccalc, l\_perppar, l\_newmap, l\_update\_b, l\_rmstest, l\_non\_rot, l\_rot\_ic, l\_sric, l\_corr, l\_rot\_ma, l\_conv\_nl, l\_dtbmovie, l\_lcr, l\_am, l\_rmagspec, l\_storevpot, l\_cond\_ma, l\_average, l\_z10mat, l\_par, l\_hel, l\_update\_s, l\_correct\_ame, l\_movie\_oc, l\_heat\_nl, l\_cmb\_field, l\_r\_fieldt, l\_movie\_ic, l\_mag, l\_save\_out

#### **Variables**

- logic/l am [logical]
  - Switch for angular momentum calculation
- logic/l\_rmagspec [logical]
  - Switch for magnetic spectra at different depths at log times
- logic/**l\_dtb** [logical]
  - Switch to reserve memory for dtB movie
- logic/lverbose[logical]
  - Switch for detailed information about run progress
- logic/l\_srma [logical]
  - Switch to rotating OC with prescribed rot. rate
- logic/l\_storetpot [logical]
  - Switch for storing entropy field potentials
- logic/l\_power[logical]
  - Switch for power budget terms calculation
- logic/l fluxprofs [logical]
  - Switch for calculation of radial profiles of flux contributions

### • logic/l\_r\_field[logical]

Switch for radial coefficients

## • logic/l\_corrmov[logical]

Switch for North/south correlation movie (see s\_getEgeos.f)

### • logic/l\_mag\_nl [logical]

Switch off non-linear magnetic terms calculation

## • logic/l\_sric[logical]

Switch to rotating IC with prescribed rot. rate

# • logic/l\_viscbccalc[logical]

Switch for dissipation layer for stress-free BCs plots

## • logic/l\_corr[logical]

Switch off rotation

## • logic/l\_mag\_kin [logical]

Switch related for kinematic dynamo

### • logic/l storevpot [logical]

Switch for storing velocity field potentials

# • logic/l\_to[logical]

Switch for TO output in TOnhs.TAG, TOshs.TAG

## • logic/l\_rot\_ma [logical]

Switch off OC rotation

# • logic/l\_conv\_nl [logical]

Switch off non-linear convection terms

## • logic/l\_b\_nl\_icb [logical]

Switch for non-linear magnetic field at IC

## • logic/l\_perppar [logical]

Switch for calculation of rad. profiles and time series of kinetic energy perpendicular+parallel to the rotation axis

#### • logic/l\_newmap [logical]

Switch for non-linear mapping (see Bayliss and Turkel, 1990)

## • logic/l\_cond\_ma [logical]

Switch for conducting OC

## • logic/l\_r\_fieldt [logical]

Switch for radial T coefficients

## • logic/l\_cond\_ic [logical]

Switch for conducting IC

# • logic/l\_average [logical]

Switch for calculation of time-averages

## • logic/l\_rot\_ic [logical]

Switch off IC rotation

# • logic/l\_z10mat [logical]

Switch for solid body rotation

# • logic/l\_update\_s [logical]

Switch off entropy update

• logic/l\_update\_v [logical]

Switch off velocity field update

• logic/l\_dt\_cmb\_field[logical]

Switch for Bcoef files for secular variation of gauss coefs.

• logic/l\_conv [logical]

Switch off convection

• logic/l\_update\_b [logical]

Switch off magnetic field update

• logic/l\_correct\_ame [logical]

Switch for correction of equatorial angular mom.

• logic/l\_tomovie [logical]

Switch for TO movie output

• logic/l\_anel [logical]

Switch for anelastic calculation

• logic/l\_correct\_amz [logical]

Switch for correction of axial angular momentum

• logic/l\_isothermal[logical]

Switch for isothermal calculation

• logic/l\_movie\_oc[logical]

Switch for recording of movie files for OC

• logic/**l\_pv** [logical]

Switch for potential vorticity calculation

• logic/l\_anelastic\_liquid[logical]

Switch for anelastic liquid calculation

• logic/l\_mag\_lf [logical]

Switch off Lorentz force term

• logic/l\_true\_time [logical]

Switch for times of outputs

• logic/l\_storepot [logical]

Switch for storing all field potentials

• logic/l\_non\_rot [logical]

Switch to non-rotating

• logic/l runtimelimit [logical]

Switch for absolute time limit of the run

• logic/l\_time\_hits [logical]

Switch for time for outputs

• logic/l\_dtbmovie [logical]

Switch for dtB movie

• logic/l\_rmstest [logical]

Switch for test of RMS balances (geostrophic, magnetostrophic, archimedean)

• logic/**l\_ht** [logical]

Switch for heat flux movie frame output

• logic/l\_heat\_nl [logical]

Switch off non-linear heat terms calculation

• logic/l\_movie [logical]

Switch for recording of movie files

• logic/l\_storebpot [logical]

Switch for storing magnetic field potentials

• logic/l\_cmb\_field[logical]

Switch for Bcoef files for gauss coefficients

• logic/l\_par [logical]

Switch for additional parameters calculation in s\_getEgeos.f

• logic/**l\_hel** [logical]

Switch for helicity calculation, output in misc.TAG

• logic/l\_mag[logical]

Switch off magnetic terms calculation

• logic/l\_dtrmagspec[logical]

Switch for magnetic spectra at different depths at movie output times

• logic/l\_store\_frame [logical]

Switch for storing movie frames

• logic/l\_movie\_ic[logical]

Switch for recording of movie files for IC

• logic/l\_b\_nl\_cmb [logical]

Switch for non-linear magnetic field at OC

• logic/l\_iner [logical]

Switch for inertial modes calculation

• logic/l\_rms [logical]

Switch for RMS force balances calculation

• logic/l\_htmovie [logical]

Switch for heat flux movie output

• logic/l\_drift [logical]

Switch for drift rates calculation

• logic/l\_lcr[logical]

Switch for zero electrical conductivity beyond r\_LCR

• logic/l\_save\_out [logical]

Switch off outputs

• logic/l\_heat [logical]

Switch off heat terms calculation

## 10.2.6 fields.f90

# **Description**

This module contains the potential fields and their radial derivatives

#### **Quick access**

Variables w\_lmloc\_container, dz, ddb\_ic, ddw\_lmloc, ddj\_lmloc, ddb\_ic\_lmloc, ddw, ddb\_lmloc, dw, b\_rloc, p, aj\_ic, dj\_lmloc, w\_rloc\_container, db\_rloc, dz\_lmloc, ddb\_rloc, db\_ic, ds\_rloc, z\_rloc\_container, p\_rloc, ddj\_ic\_lmloc, s\_lmloc\_container, dz\_rloc, b\_ic\_lmloc, aj\_ic\_lmloc, dj\_rloc, aj\_lmloc\_container, b, aj, z\_lmloc, w, db\_ic\_lmloc, db\_lmloc, dw\_rloc, dj\_ic\_lmloc, ds, s\_rloc, z, dp, p\_lmloc\_container, ddw\_rloc, ds\_lmloc, aj\_lmloc, p\_rloc\_container, b\_lmloc, dp\_rloc, dw\_lmloc, w\_rloc, ddj\_ic, ddj, b\_lmloc\_container, ddb, z\_lmloc\_container, p\_lmloc, dj\_ic, db, aj\_rloc\_container, aj\_rloc, s\_rloc\_container, s, z\_rloc, dp\_lmloc, b\_ic, b\_rloc\_container, dj, w\_lmloc, s\_lmloc, omega\_ma, omega\_ic

Routines initialize\_fields()

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- radial\_data(nrstop(), nrstart())
- lmloop data(ulm(), llm(), llmmag(), ulmmag())
- truncation (lm\_max(), n\_r\_max(), n\_r\_maxmag(), n\_r\_ic\_maxmag(), lm\_maxmag()): This module defines the grid points and the truncation
- parallel\_mod (rank ()): This module contains the blocking information

## **Variables**

- fields/s\_lmloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/dp(:,:) [complex,allocatable/public]
- fields/dz\_rloc(:,:) [complex,pointer/public]
- fields/omega\_ic[real,public]
- fields/w\_lmloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/ds\_rloc(:,:) [complex,pointer/public]
- fields/**ds**(:,:) [complex,allocatable/public]
- fields/s\_rloc(:,:) [complex,pointer/public]
- fields/dz (:,:) [complex,allocatable/public]
- fields/p\_lmloc(:,:) [complex,pointer/public]
- fields/**z**(:,:) [complex,allocatable/public]
- fields/dw\_lmloc(:,:) [complex,pointer/public]
- fields/dj\_ic(:,:) [complex,allocatable/public]
- fields/b\_rloc(:,:) [complex,pointer/public]
- fields/p\_lmloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/b\_ic\_lmloc(:,:) [complex,allocatable/public]

- fields/ddw\_rloc(:,:) [complex,pointer/public]
- fields/ddb\_ic(:,:) [complex,allocatable/public]
- fields/**z\_rloc\_container** (:,:,:) [complex,target/allocatable/public]
- fields/p(:,:) [complex,allocatable/public]
- fields/ddw lmloc(:,:) [complex,pointer/public]
- fields/ddj\_ic(:,:) [complex,allocatable/public]
- fields/db (:,:) [complex,allocatable/public]
- fields/ddj\_lmloc(:,:) [complex,pointer/public]
- fields/omega\_ma[real,public]
- fields/ds\_lmloc(:,:) [complex,pointer/public]
- fields/p\_rloc(:,:) [complex,pointer/public]
- fields/**z\_rloc**(:,:) [complex,pointer/public]
- fields/dp\_lmloc(:,:) [complex,pointer/public]
- fields/aj\_ic(:,:) [complex,allocatable/public]
- fields/aj\_lmloc(:,:) [complex,pointer/public]
- fields/dj rloc(:,:) [complex,pointer/public]
- fields/aj\_lmloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/p\_rloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/ddb\_ic\_lmloc(:,:) [complex,allocatable/public]
- fields/ddj\_ic\_lmloc(:,:) [complex,allocatable/public]
- fields/aj\_rloc(:,:) [complex,pointer/public]
- fields/w\_rloc(:,:) [complex,pointer/public]
- fields/aj\_ic\_lmloc(:,:) [complex,allocatable/public]
- fields/dj\_lmloc(:,:) [complex,pointer/public]
- fields/w\_rloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/**ddb** (:,:) [complex,allocatable/public]
- fields/aj\_rloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/b\_rloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/dj(:,:) [complex,allocatable/public]
- fields/aj(:,:) [complex,allocatable/public]
- fields/**z\_lmloc**(:,:) [complex,pointer/public]
- fields/b(:,:) [complex,allocatable/public]
- fields/w(:,:) [complex,allocatable/public]
- fields/ddj(:,:) [complex,allocatable/public]
- fields/b\_lmloc(:,:) [complex,pointer/public]
- fields/b\_lmloc\_container(:,:,:) [complex,target/allocatable/public]

- fields/ddw(:,:) [complex,allocatable/public]
- fields/s\_rloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/db\_rloc(:,:) [complex,pointer/public]
- fields/dz\_lmloc(:,:) [complex,pointer/public]
- fields/ddb lmloc(:,:) [complex,pointer/public]
- fields/ddb\_rloc(:,:) [complex,pointer/public]
- fields/s(:,:) [complex,allocatable/public]
- fields/s\_lmloc(:,:) [complex,pointer/public]
- fields/dp\_rloc(:,:) [complex,pointer/public]
- fields/db\_lmloc(:,:) [complex,pointer/public]
- fields/**b\_ic**(:,:) [complex,allocatable/public]
- fields/dw\_rloc(:,:) [complex,pointer/public]
- fields/dj\_ic\_lmloc(:,:) [complex,allocatable/public]
- fields/db\_ic\_lmloc(:,:) [complex,allocatable/public]
- fields/w\_lmloc(:,:) [complex,pointer/public]
- fields/dw(:,:) [complex,allocatable/public]
- fields/db\_ic(:,:) [complex,allocatable/public]
- fields/z\_lmloc\_container(:,:,:) [complex,target/allocatable/public]

Routines initialize\_fieldslast()

# 10.2.7 dt fieldsLast.f90

## **Description**

This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.

The variables labeled with a suffix 'Last' are provided by the restart file for the first time step or calculated here or by the update routines for the following time step. These fields remain in the LM-distributed space

# **Quick access**

```
Variables dbdtlast, dpdtlast, dwdtlast, dzdtlast, djdtlast, dbdtlast_lmloc, dzdtlast_lo, dsdtlast, djdt_iclast, dwdtlast_lmloc, djdt_iclast_lmloc, dsdtlast_lmloc, djdtlast_lmloc, dbdt_iclast, dbdt_iclast_lmloc, dpdtlast_lmloc, lorentz_torque_iclast, lorentz_torque_malast, d_omega_ma_dtlast, d_omega_ic_dtlast
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- lmloop\_data(ulm(), llm(), llmmag(), ulmmag())
- truncation(lm\_max(), n\_r\_max(), n\_r\_maxmag(), n\_r\_ic\_maxmag(), lm\_maxmag()): This module defines the grid points and the truncation
- parallel\_mod (rank ()): This module contains the blocking information

#### **Variables**

- fieldslast/djdt\_iclast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/dzdtlast\_lo(:,:) [complex,allocatable/public]
- fieldslast/lorentz\_torque\_malast [real,public]
- fieldslast/dzdtlast(:,:) [complex,allocatable/public]
- fieldslast/djdtlast(:,:) [complex,allocatable/public]
- fieldslast/dwdtlast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/djdt\_iclast (:,:) [complex,allocatable/public]
- fieldslast/dsdtlast(:,:) [complex,allocatable/public]
- fieldslast/dsdtlast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/dpdtlast(:,:) [complex,allocatable/public]
- fieldslast/dbdtlast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/dbdtlast(:,:) [complex,allocatable/public]
- fieldslast/d\_omega\_ic\_dtlast [real, public]
- fieldslast/lorentz\_torque\_iclast [real,public]
- fieldslast/dbdt\_iclast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/djdtlast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/dpdtlast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/d\_omega\_ma\_dtlast [real,public]
- fieldslast/dwdtlast(:,:) [complex,allocatable/public]
- fieldslast/dbdt\_iclast(:,:) [complex,allocatable/public]

## **Subroutines and functions**

Called from magic

# 10.2.8 mat.f90

## **Description**

This module contains matricies for internal time step

#### **Quick access**

```
Variables z10mat_fac, smat, zmat_fac, smat_fac, z10mat, bmat, wpmat, zmat, bmat_fac, jmat_fac, jmat, wpmat_fac, s0mat_fac, s0mat, lwpmat, spivot, lsmat, lbmat, s0pivot, bpivot, wppivot, zpivot, jpivot, z10pivot, lzmat, lz10mat
```

Routines initialize\_matrices()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- truncation (l\_maxmag(), n\_r\_max(), l\_max(), n\_r\_totmag(), n\_r\_tot()): This module defines the grid points and the truncation

#### **Variables**

- matrices/**z10pivot** (:) [integer,allocatable/public]
- matrices/smat\_fac(:,:) [real,allocatable/public]
- matrices/wpmat\_fac(:,:,:) [real,allocatable/public]
- matrices/**spivot** (:,:) [integer,allocatable/public]
- matrices/jmat(:,:,:) [real,allocatable/public]
- matrices/**zmat\_fac**(:,:) [real,allocatable/public]
- matrices/lz10mat [logical,public]
- matrices/s0mat\_fac(:)[real,allocatable/public]
- matrices/bmat(:,:,:) [real,allocatable/public]
- matrices/s0mat(:,:) [real,allocatable/public]
- matrices/wpmat (:,:,:) [real,allocatable/public]
- matrices/jpivot(:,:) [integer,allocatable/public]
- matrices/z10mat\_fac(:)[real,allocatable/public]
- matrices/**zmat**(:,:,:) [real,allocatable/public]
- matrices/**z10mat** (:,:) [real,allocatable/public]
- matrices/**zpivot** (:,:) [integer,allocatable/public]
- matrices/lbmat(:)[logical,allocatable/public]
- matrices/bmat\_fac(:,:) [real,allocatable/public]
- matrices/lsmat(:) [logical,allocatable/public]

- matrices/jmat\_fac(:,:) [real,allocatable/public]
- matrices/lwpmat (:) [logical,allocatable/public]
- matrices/smat(:,:,:) [real,allocatable/public]
- matrices/wppivot (:,:) [integer,allocatable/public]
- matrices/s0pivot(:)[integer,allocatable/public]
- matrices/bpivot (:,:) [integer,allocatable/public]
- matrices/lzmat(:)[logical,allocatable/public]

subroutine matrices/initialize matrices()

Called from magic

# 10.2.9 output\_data.f90

### **Description**

This module contains the parameters for output control

#### **Quick access**

Variables nzmaxa, nsmaxa, n time hits, b r file, t r file, v r file, dt\_cmb\_file, perppar\_file, rst\_file, rot\_file, e\_kin\_file, dtvasrms\_file, dipole\_file, srma\_file, par\_file, u\_square\_file, e\_mag\_oc\_file, dtdrms\_file, lp\_file, graph\_file, e\_mag\_ic\_file, log\_file, dtbrms\_file, cmbmov\_file, power\_file, dtvrms\_file, runid, cmb\_file, misc\_file, tag, angular\_file, sric\_file, t\_pot, t\_to, t\_bpot, t\_vpot, t\_rst, t\_r\_field, t\_movie, t\_graph, t\_tpot, t\_spec, t\_cmb, t\_tomovie, t\_toz, t\_log, n\_r\_array, n\_b\_r\_file, n\_v\_r\_file, n\_coeff\_r, n\_t\_r\_file, rcut, dt\_bpot, rdea, dt\_tpot, t\_pot\_stop, dt\_cmb, t\_pot\_start, dt\_spec, t\_graph\_start, dt\_log, t\_spec\_start, t\_movie\_start, t\_rst\_start, t\_bpot\_stop, dt\_movie, sdens, t\_tomovie\_stop, t\_cmb\_stop, t\_toz\_start, t\_graph\_stop, dt\_pot, t\_tomovie\_start, dt\_r\_field, t\_rst\_stop, t\_vpot\_start, t\_tpot\_stop, dt\_vpot, dt\_tomovie, t\_log\_start, dt\_to, t\_r\_field\_stop, t\_cmb\_start, dt\_graph, t\_r\_field\_start, zdens, t\_bpot\_start, t\_log\_stop, dt\_toz, t\_to\_stop, t\_tpot\_start, t\_vpot\_stop, t\_to\_start, t\_movie\_stop, t\_toz\_stop, dt\_rst, t\_spec\_stop, n\_pots, n\_u2\_spec\_file, n\_coeff\_r\_max, n\_u\_square\_file, l\_max\_r, n\_cmbmov\_file, n\_srma\_file, l\_max\_cmb, n\_log\_file, n\_bpots, rst\_mpi\_fh, n\_t\_cmb, n\_graph\_step, n\_tozs, n\_e\_mag\_ic\_file, n\_logs, n\_cmb\_step, n\_power\_file, n\_signal\_file, n\_par\_file, n\_dtbrms\_file, n\_dt\_cmb\_file, n tomovie frames, n\_rst\_file, n\_bpot\_step, n\_rst\_step, n\_sric\_file, n\_vpot\_step, n\_misc\_file, n\_perppar\_file, n\_log\_step, n\_spec\_step, n\_dtvrms\_file, graph\_mpi\_fh, n\_t\_toz, n\_tpot\_step, n\_r\_fields, n\_tomovie\_step, n\_t\_rst, n\_angular\_file, n\_t\_pot, n\_graphs, n\_r\_step, n\_t\_tomovie, n\_pot\_step, n\_movie\_step, n\_e\_kin\_file, n\_e\_mag\_oc\_file, n\_lp\_file, n\_tos, n\_rot\_file, n\_dtdrms\_file, n\_t\_r\_field, n\_tpots, n\_t\_spec, n\_cmbs,

```
l_graph_time, n_stores, n_dtvasrms_file, n_cmb_file, n_kin_spec_file, n_r_field_step, n_dipole_file, n_t_graph, n_toz_step, n_specs, n_rsts, n_t_movie, n_t_tpot, n_t_log, n_t_to, n_to_step, n_t_bpot, n_graph_file, n_mag_spec_file, nlf, n_t_vpot, n_vpots, n_movie_frames
```

Routines openfiles(), closefiles()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- charmanip (length\_to\_blank()): This module contains several useful routines to manipule character strings
- logic (l\_perppar(), l\_r\_fieldt(), l\_cmb\_field(), l\_dt\_cmb\_field(), l\_am(), l\_power(), l\_rms(), l\_anel(), l\_rot\_ic(), l\_movie(), l\_rot\_ma(), l\_mag(), l\_save\_out(), l\_r\_field(), l\_sric(), l\_rmstest(), l\_srma()): Module containing the logicals that control the run
- parallel\_mod (rank ()): This module contains the blocking information

### **Variables**

- output\_data/t\_rst\_stop [real,public]
- output\_data/angular\_file [character,public]
- output\_data/n\_e\_mag\_oc\_file [integer,public]
- output\_data/n\_coeff\_r(:) [integer,allocatable/public]
- output\_data/n\_tomovie\_frames [integer,public]
- output\_data/n\_vpot\_step [integer,public]
- output\_data/t\_r\_field\_start [real,public]
- output\_data/n\_rst\_file [integer,public]
- output\_data/dt\_spec [real,public]
- output\_data/n\_lp\_file [integer,public]
- output\_data/power\_file [character,public]
- output\_data/n\_par\_file [integer,public]
- output\_data/zdens [real,public]
- output\_data/t\_graph\_start [real,public]
- output\_data/n\_dt\_cmb\_file [integer,public]
- output\_data/n\_pots[integer,public]
- output\_data/e\_mag\_ic\_file [character,public]
- output\_data/t\_bpot\_start [real,public]
- output\_data/dtvrms\_file [character,public]
- output\_data/t\_log\_stop [real,public]
- output\_data/n\_coeff\_r\_max [integer,public]

- output\_data/n\_e\_mag\_ic\_file [integer, public]
- output\_data/t\_vpot (5000) [real,public]
- output\_data/n\_u2\_spec\_file [integer,public]
- output\_data/t\_pot\_start [real,public]
- output\_data/n\_tos[integer,public]
- output data/dt cmb file [character, public]
- output\_data/n\_kin\_spec\_file [integer,public]
- output\_data/n\_t\_graph [integer,public]
- output\_data/dipole\_file [character,public]
- output\_data/n\_toz\_step[integer,public]
- output\_data/t\_vpot\_start [real,public]
- output\_data/n\_dipole\_file [integer,public]
- output\_data/t\_cmb (5000) [real,public]
- output\_data/n\_u\_square\_file [integer,public]
- output\_data/n\_specs [integer,public]
- output\_data/n\_rot\_file [integer,public]
- output\_data/n\_rsts[integer,public]
- output\_data/runid[character,public]
- output\_data/n\_b\_r\_file (:) [integer,allocatable/public]
- output\_data/l\_max\_r [integer,public]
- output\_data/t\_r\_field(5000)[real,public]
- output\_data/n\_rst\_step[integer,public]
- output\_data/n\_logs [integer,public]
- output\_data/n\_dtdrms\_file [integer,public]
- output\_data/n\_graph\_file [integer,public]
- output\_data/n\_mag\_spec\_file [integer,public]
- output\_data/t\_spec\_start [real,public]
- output\_data/n\_cmbmov\_file [integer,public]
- output\_data/dt\_pot [real,public]
- output\_data/n\_sric\_file [integer,public]
- output\_data/n\_t\_movie [integer,public]
- output\_data/dt\_r\_field[real,public]
- output\_data/n\_bpot\_step[integer,public]
- output\_data/t\_rst\_start [real,public]
- output\_data/n\_srma\_file [integer,public]
- output\_data/dt\_cmb [real,public]

- output\_data/n\_t\_tpot [integer,public]
- output\_data/nsmaxa[integer,parameter=97/public]
- output\_data/b\_r\_file(:)[character,allocatable/public]
- output\_data/n\_misc\_file [integer,public]
- output\_data/t\_to\_stop [real,public]
- output\_data/t\_r\_file(:) [character,allocatable/public]
- output\_data/t\_pot (5000) [real,public]
- output\_data/n\_t\_spec [integer,public]
- output\_data/t\_tomovie (5000) [real,public]
- output\_data/t\_bpot\_stop [real,public]
- output\_data/perppar\_file [character,public]
- output\_data/n\_t\_log[integer,public]
- output\_data/dt\_bpot [real,public]
- output\_data/rdea [real,public]
- output\_data/n\_cmbs [integer,public]
- output\_data/l\_graph\_time [logical,public]
- output\_data/dtdrms\_file [character,public]
- output\_data/l\_max\_cmb [integer,public]
- output\_data/t\_log(5000)[real,public]
- output\_data/dt\_tomovie [real,public]
- output\_data/t\_tomovie\_stop [real,public]
- output\_data/rst\_file [character,public]
- output\_data/n\_t\_cmb [integer,public]
- output\_data/t\_movie\_stop [real,public]
- output\_data/n\_t\_to[integer,public]
- output\_data/t\_tpot\_start [real,public]
- output\_data/n\_dtbrms\_file [integer,public]
- output\_data/t\_tpot\_stop [real,public]
- output\_data/n\_power\_file[integer,public]
- output\_data/dt\_log[real,public]
- output\_data/n\_log\_step[integer,public]
- output\_data/t\_movie\_start [real,public]
- output\_data/t\_movie (5000) [real, public]
- output\_data/n\_t\_tomovie [integer,public]
- output\_data/misc\_file [character,public]
- output\_data/rot\_file [character,public]

- output\_data/t\_to (5000) [real, public]
- output\_data/n\_dtvrms\_file [integer,public]
- output\_data/t\_graph (5000) [real,public]
- output\_data/dt\_tpot [real,public]
- output\_data/tag[character,public]
- output data/nzmaxa[integer,parameter=194/public]
- output\_data/srma\_file [character,public]
- output\_data/graph\_mpi\_fh [integer, public]
- output\_data/n\_t\_toz [integer,public]
- output\_data/n\_stores [integer,public]
- output\_data/log\_file [character,public]
- output\_data/dt\_to [real,public]
- output\_data/n\_graph\_step[integer,public]
- output\_data/cmbmov\_file [character,public]
- output\_data/n\_tozs[integer,public]
- output\_data/e\_kin\_file [character,public]
- output\_data/n\_log\_file [integer,public]
- output\_data/n\_bpots[integer,public]
- output\_data/n\_tpot\_step[integer,public]
- output\_data/n\_v\_r\_file (:) [integer,allocatable/public]
- output\_data/t\_toz\_start [real,public]
- output\_data/n\_dtvasrms\_file [integer,public]
- output\_data/t\_bpot (5000) [real,public]
- output\_data/n\_r\_step [integer,public]
- output\_data/t\_toz (5000) [real,public]
- output\_data/t\_tomovie\_start [real,public]
- output\_data/n\_t\_bpot [integer,public]
- output\_data/n\_r\_array (100) [integer,public]
- output\_data/e\_mag\_oc\_file [character,public]
- output\_data/n\_tomovie\_step [integer,public]
- output\_data/n\_t\_rst[integer,public]
- output\_data/lp\_file [character,public]
- output\_data/n\_t\_r\_field[integer,public]
- output\_data/par\_file [character,public]
- output\_data/nlf[integer,public]
- output\_data/t\_pot\_stop [real,public]

- output\_data/graph\_file [character,public]
- output\_data/dtbrms\_file [character,public]
- output\_data/t\_log\_start [real,public]
- output\_data/n\_tpots[integer,public]
- output\_data/rcut [real,public]
- output\_data/n\_perppar\_file [integer,public]
- output\_data/t\_graph\_stop [real,public]
- output\_data/dt\_toz[real,public]
- output\_data/n\_cmb\_step [integer,public]
- output\_data/t\_spec (5000) [real,public]
- output\_data/sdens [real,public]
- output\_data/t\_cmb\_stop [real,public]
- output\_data/t\_tpot (5000) [real,public]
- output\_data/rst\_mpi\_fh [integer,public]
- output\_data/dtvasrms\_file [character,public]
- output\_data/t\_r\_field\_stop [real,public]
- output\_data/u\_square\_file [character,public]
- output\_data/t\_cmb\_start [real,public]
- output\_data/dt\_movie [real,public]
- output\_data/n\_e\_kin\_file [integer,public]
- output\_data/n\_signal\_file [integer,public]
- output\_data/sric\_file [character,public]
- output\_data/t\_rst (5000) [real,public]
- output\_data/n\_cmb\_file [integer,public]
- output\_data/dt\_rst [real,public]
- output\_data/dt\_graph [real,public]
- output\_data/cmb\_file [character,public]
- output\_data/dt\_vpot [real,public]
- output\_data/n\_t\_pot [integer,public]
- output\_data/n\_pot\_step[integer,public]
- output\_data/t\_vpot\_stop [real,public]
- output\_data/n\_time\_hits [integer,parameter=5000/public]
- output\_data/n\_t\_r\_file (:) [integer,allocatable/public]
- output\_data/n\_movie\_step[integer,public]
- output\_data/t\_to\_start [real,public]
- output\_data/t\_toz\_stop [real,public]

- output\_data/n\_r\_field\_step[integer,public]
- output\_data/n\_r\_fields [integer,public]
- output\_data/n\_angular\_file [integer,public]
- output\_data/n\_vpots [integer,public]
- output\_data/n\_graphs [integer,public]
- output\_data/v\_r\_file (:) [character,allocatable/public]
- output\_data/n\_t\_vpot [integer,public]
- output\_data/n\_to\_step[integer,public]
- output\_data/t\_spec\_stop [real,public]
- output\_data/n\_spec\_step [integer,public]
- output\_data/n\_movie\_frames [integer,public]

```
subroutine output_data/openfiles()
```

Defines names and unit for output files and opens then.

Called from magic

Call to length\_to\_blank()

subroutine output\_data/closefiles()

Defines names and unit for output files and opens then. MPI: called only by the processor responsible for output.

Called from magic

# 10.2.10 Bext.f90

# **Description**

Module containing the external field parameters

### **Quick access**

```
Variables fac_loop, rrmp, amp_curr, bmax_imp, expo_imp, amp_imp, n_imp, l_imp, l_curr
```

#### **Needed modules**

• precision\_mod: This module controls the precision used in MagIC

### **Variables**

- bext/amp\_imp [real]
  Amplitude of the time varying osc
- bext/l\_imp [integer]
   Mode of external field (dipole,quadrupole etc.)
- bext/amp\_curr [real]
  Amplitude of magnetic field of current loop
- bext/bmax\_imp [real]
  Location of maximum in g\_ext/g\_int
- bext/1\_curr [logical]
   Switch for current loop at the equator
- bext/**rrmp** [real]

  Magnetopause radius
- bext/fac\_loop(:)[real,allocatable]
- bext/n\_imp [integer]
  Controls external field model
- bext/expo\_imp [real]
  Exponent for decay

# 10.2.11 constants.f90

## **Description**

module containing constants and parameters used in the code.

## **Quick access**

Variables codeversion, third, osq4pi, sq4pi, cos72, cos36, sin72, sin36, ci, one, two, sin60, half, zero, four, three, pi, c\_lorentz\_ma, surf\_cmb, mass, y10\_norm, c\_moi\_ma, c\_z10\_omega\_ma, c\_z10\_omega\_ic, c\_lorentz\_ic, c\_moi\_ic, c\_dt\_z10\_ma, vol\_ic, y11\_norm, vol\_oc, c\_dt\_z10\_ic, c\_moi\_oc

#### **Needed modules**

• precision\_mod: This module controls the precision used in MagIC

## **Variables**

- constants/three [real,parameter=3.0\_cp]
- constants/c\_moi\_ma [real]

  Moment of inertia of the mantle
- constants/half [real,parameter=0.5\_cp]
- constants/c\_z10\_omega\_ic[real]

- constants/sin60 [real,parameter=0.5\_cp\*sqrt(3.0\_cp)]
- constants/pi [real,parameter=4.0\_cp\*atan(1.0\_cp)]
- constants/cos72 [real,parameter=cos(72.0\_cp\*pi/180.0\_cp)]
- constants/c\_moi\_ic[real]

Moment of inertia of the inner core

- constants/**four** [real,parameter=4.0 cp]
- constants/codeversion [character,parameter='5.1']
- constants/ci [complex,parameter=(0.0\_cp,1.0\_cp)]
- constants/c\_dt\_z10\_ma [real]
- constants/sin36 [real, parameter= $sin(36.0_cp*pi/180.0_cp)$ ]
- constants/c\_dt\_z10\_ic[real]
- constants/vol\_oc[real]

Volume of the outer core

- constants/**third**[real,parameter=onelthree]
- constants/**two** [real,parameter=2.0\_cp]
- constants/osq4pi [real,parameter=1.0\_cp/sq4pi]
- constants/**surf** cmb [real] Outer boundary surface
- constants/one [real,parameter=1.0\_cp]
- constants/sin72 [real,parameter=sin(72.0\_cp\*pi/180.0\_cp)]
- constants/**sq4pi** [real,parameter=sqrt(4.0\_cp\*pi)]
- constants/**vol\_ic**[real] Volume of the inner core

- constants/c\_lorentz\_ic [real]
- constants/**zero** [complex,parameter=(0.0\_cp,0.0\_cp)]
- constants/mass[real]

Mass of the outer core

• constants/c moi oc[real]

Moment of inertia of the outer core

- constants/y11\_norm[real]
- constants/c\_lorentz\_ma [real]
- constants/y10\_norm[real]
- constants/c\_z10\_omega\_ma[real]
- constants/cos36 [real,parameter=cos(36.0\_cp\*pi/180.0\_cp)]

# 10.2.12 Grenoble.f90

# **Description**

This module contains all variables for the case of an imposed IC dipole

#### **Quick access**

```
Variables b0, ddb0, db0, bic, lgrenoble
Routines initialize_grenoble()
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- truncation (n\_r\_maxmag()): This module defines the grid points and the truncation

#### **Variables**

- grenoble/b0 (:) [real,allocatable/public]
- grenoble/bic[real,public]
- grenoble/lgrenoble [logical,public]
- grenoble/ddb0 (:) [real,allocatable/public]
- grenoble/db0 (:) [real,allocatable/public]

#### Subroutines and functions

```
subroutine grenoble/initialize_grenoble()
Called from magic
```

# 10.3 MPI related modules

# 10.3.1 parallel.f90

# **Description**

This module contains the blocking information

#### **Quick access**

```
Variables nr_per_rank, n_procs, chunksize, ierr, nlmbs_per_rank,
    rank_with_l1m0, nthreads, nr_on_last_rank, rank_bn
Routines parallel()
```

#### **Needed modules**

- mpi
- omp\_lib

#### **Variables**

- parallel\_mod/nr\_on\_last\_rank [integer]
- parallel\_mod/rank\_bn [integer]
- parallel\_mod/chunksize [integer]
- parallel\_mod/n\_procs [integer]
- parallel\_mod/ierr[integer]
- parallel\_mod/nthreads [integer]
- parallel\_mod/nlmbs\_per\_rank [integer]
- parallel\_mod/rank\_with\_l1m0 [integer]
- parallel\_mod/nr\_per\_rank [integer]

## **Subroutines and functions**

```
subroutine parallel_mod/parallel()
```

Called from magic

## 10.3.2 radial data.f90

#### **Quick access**

```
Variables nrstop, nrstartmag, nrstart, n_r_icb, n_r_cmb, nrstopmag

Routines initialize_radial_data()
```

### **Needed modules**

- logic (l\_maq(), lverbose()): Module containing the logicals that control the run
- truncation (n\_r\_max()): This module defines the grid points and the truncation
- parallel\_mod(n\_procs(), nr\_on\_last\_rank(), rank(), nr\_per\_rank()): This module contains the blocking information

# **Variables**

- radial\_data/n\_r\_icb [integer,public]
- radial\_data/nrstop[integer,public]
- radial\_data/nrstopmag[integer,public]

- radial\_data/nrstartmag[integer,public]
- radial\_data/n\_r\_cmb [integer,public]
- radial\_data/nrstart[integer,public]

```
subroutine radial_data/initialize_radial_data()
Called from magic
```

# 10.3.3 LMLoop\_data.f90

#### **Quick access**

```
Variables lm_per_rank, lm_on_last_rank, llm, llmmag, ulm, ulmmag
Routines initialize_lmloop_data()
```

#### **Needed modules**

- blocking (lmstartb(), nlmbs(), sizelmb(), lmstopb()): Module containing blocking information
- logic (l\_mag()): Module containing the logicals that control the run
- parallel\_mod(n\_procs(), nlmbs\_per\_rank(), rank()): This module contains the blocking information

## **Variables**

- lmloop\_data/ulm[integer,public]
- lmloop\_data/llmmag[integer,public]
- lmloop\_data/lm\_per\_rank [integer,public]
- lmloop\_data/llm[integer,public]
- lmloop\_data/ulmmag[integer,public]
- lmloop\_data/lm\_on\_last\_rank [integer,public]

# Subroutines and functions

```
subroutine lmloop_data/initialize_lmloop_data()
Called from magic
```

# 10.3.4 communications.f90

#### Quick access

```
temp_gather_lo, r_transfer_type_nr_end, ses, r_request, s_transfer_type_nr_end,
Variables temp r210,
   array_of_statuses,
   r_transfer_type_cont,
                              s_transfer_type,
                                                      final_wait_array,
   s_transfer_type_cont, s_transfer_type_nr_end_cont, s_request,
   r_transfer_type_nr_end_cont, r_transfer_type, get_global_sum,
   102r_aj, gt_cheb, gt_oc, 102r_s, gt_ic, 102r_p, 102r_z, 102r_w, 102r_b,
   r_lm_gather_type_lm_end, r_lm_gather_type
Routines myallgather(), get_global_sum_cmplx_1d(), get_global_sum_real_2d(),
   get_global_sum_cmplx_2d(), create_gather_type(), destroy_lm2r_type(),
   initialize_communications(), lm2r_redist_wait(), lo2lm_redist(),
   scatter_from_rank0_to_lo(),
                                                  destroy_gather_type(),
   lm2r_redist_start(), lo2r_redist_wait(), gather_from_lo_to_rank0(),
   gather_all_from_lo_to_rank0(), r2lo_redist(), lo2r_redist_start(),
   lm2lo_redist(), create_lm2r_type(), r2lm_redist()
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- logic(l\_mag(), l\_heat(), l\_conv()): Module containing the logicals that control the run
- blocking (st\_map(), lmstartb(), lo\_map(), lmstopb()): Module containing blocking information
- mpi
- lmloop\_data(ulm(), llm())
- truncation(lm\_max(), n\_r\_max(), l\_max(), minc(), n\_r\_ic\_max()): This module defines the grid points and the truncation
- radial\_data(nrstop(), nrstart())
- parallel\_mod (n\_procs(), nr\_on\_last\_rank(), rank(), nr\_per\_rank(), ierr()): This module contains the blocking information

## **Types**

• type communications/unknown\_type

## Type fields

- % temp\_rloc(,,\*)[complex,pointer]
- % arr\_rloc (,,\*) [complex,pointer]
- % s\_request (\*) [integer,allocatable]
- % final wait array (\*) [integer, allocatable]
- % r\_request (\*) [integer, allocatable]
- % count [integer]
- type communications/unknown\_type

# Type fields

- % gather\_mpi\_type (\*) [integer,allocatable]
- % dim2 [integer]

#### **Variables**

- communications/**gt\_ic**[gather\_type,public]
- communications/final\_wait\_array(:)[integer,private/allocatable]
- communications/r\_transfer\_type(:)[integer,private/allocatable/save]
- communications/lo2r\_b [lm2r\_type,public]
- communications/array\_of\_statuses(:,:) [integer,private/allocatable]
- communications/r\_request(:) [integer,private/allocatable]
- communications/s\_transfer\_type\_nr\_end(:) [integer,private/allocatable/save]
- communications/r\_lm\_gather\_type [integer,private]
- communications/lo2r\_z [lm2r\_type,public]
- communications/s\_transfer\_type\_cont(:,:) [integer,private/allocatable/save]
- communications/lo2r\_w [lm2r\_type,public]
- communications/lo2r\_aj[lm2r\_type,public]
- communications/r\_transfer\_type\_cont (:,:) [integer,private/allocatable/save]
- communications/s\_transfer\_type\_nr\_end\_cont (:,:) [integer,private/allocatable/save]
- communications/lo2r\_s [lm2r\_type,public]
- communications/**s\_request**(:) [integer,private/allocatable]
- communications/temp\_r2lo(:,:) [complex,private/allocatable]
- communications/lo2r\_p[lm2r\_type,public]
- communications/r\_transfer\_type\_nr\_end\_cont (:,:) [integer,private/allocatable/save]
- communications/get\_global\_sum[public]
- communications/**gt\_cheb** [gather\_type,public]
- communications/r\_lm\_gather\_type\_lm\_end[integer,private]
- communications/**s\_transfer\_type**(:) [integer,private/allocatable/save]
- communications/temp\_gather\_lo(:) [complex,private/allocatable]
- communications/gt\_oc [gather\_type,public]
- communications/r\_transfer\_type\_nr\_end(:) [integer,private/allocatable/save]

#### **Subroutines and functions**

```
subroutine communications/initialize_communications()
```

Called from magic

Call to create\_gather\_type(), create\_lm2r\_type()

```
function communications/get_global_sum_cmplx_2d (dwdt_local)
```

Parameters dwdt local (,) [complex,in]

Return global\_sum [real]

function communications/get\_global\_sum\_real\_2d (dwdt\_local)

Parameters dwdt local (,) [real,in]

Return global sum [real]

function communications/get\_global\_sum\_cmplx\_1d(arr\_local)

# Kahan summation algorithm

```
function KahanSum(input)
var sum = 0.0
var c = 0.0
                       //A running compensation for lost low-order bits.
for i = 1 to input.length do
  y = input[i] - c //So far, so good: c is zero.
  t = sum + y
                      //Alas, sum is big, y small,
                      //so low-order digits of y are lost.
  c = (t - sum) - y //(t - sum) recovers the high-order part of y;
                      //subtracting y recovers - (low part of y)
                      //Algebraically, c should always be zero.
  sum = t
                      //Beware eagerly optimising compilers!
  //Next time around, the lost low part will be added to y in a fresh attempt.
return sum
```

Parameters arr local (\*) [complex,in]

**Return global\_sum** [real]

subroutine communications/gather\_all\_from\_lo\_to\_rank0 (self, arr\_lo, arr\_full)

## **Parameters**

- **self** [gather\_type]
- arr\_lo (ulm-(llm)+1,self%dim2) [complex]
- arr\_full (lm\_max,self%dim2) [complex]

```
Called from outto(), getegeos(), get_dtblmfinish(), output(),
  fields_average(), outpv()
```

subroutine communications/create\_gather\_type (self, dim2)

Define the datatypes for gather\_all\_from\_lo\_to\_rank0 the sending array has dimension (llm:ulm,1:dim2) receiving array has dimension (1:lm\_max,1:dim2)

# **Parameters**

- self [gather\_type]
- dim2 [integer]

Called from initialize\_communications()

subroutine communications/destroy\_gather\_type (self)

**Parameters self** [gather\_type]

subroutine communications/gather\_from\_lo\_to\_rank0 (arr\_lo, arr\_full)

```
Parameters
               • arr lo (ulm-(llm)+1) [complex]
               • arr_full (lm_max) [complex]
         Called from storepotw(), fields_average()
subroutine communications/scatter from rank0 to lo(arr full, arr lo)
         Parameters
               • arr_full (lm_max) [complex]
               • arr_lo (ulm-(llm)+1) [complex]
         Called from getstartfields()
subroutine communications/create_lm2r_type (self[, count])
         Parameters self [lm2r_type]
         Options count [integer,in,optional]
         Called from initialize_communications()
subroutine communications/destroy_lm2r_type (self)
         Parameters self [lm2r_type]
subroutine communications/lm2r redist start(self, arr lmloc, arr rloc)
         Parameters
               • self [lm2r_type]
               • arr_lmloc (ulm-(llm)+1,n_r_max,*) [complex,in]
               • arr_rloc (lm_max,nrstop-(nrstart)+1,*) [complex,out]
         Called from lo2r_redist_start()
subroutine communications/lm2r_redist_wait (self)
         Parameters self [lm2r_type]
         Called from 102r redist wait()
subroutine communications/lo2r redist start (self, arr lo, arr rloc)
         Parameters
               • self [lm2r_type]
               • arr_lo (ulm-(llm)+1,n_r_max,*) [complex,in]
               • arr_rloc (lm_max,nrstop-(nrstart)+1,*) [complex,out,target]
         Called from getstartfields(), lmloop()
         Call to lm2r_redist_start()
subroutine communications/lo2r_redist_wait (self)
         Parameters self [lm2r_type]
         Called from step_time()
         Call to lm2r_redist_wait()
subroutine communications/r2lm_redist (arr_rloc, arr_lmloc)
```

#### **Parameters**

- arr\_rloc (lm\_max,nrstop-(nrstart)+1) [complex,in]
- arr\_lmloc (ulm-(llm)+1,n\_r\_max) [complex,out]

Called from r2lo\_redist()

subroutine communications/r2lo redist(arr rloc, arr lo)

#### **Parameters**

- arr\_rloc (lm\_max,nrstop-(nrstart)+1) [complex,in]
- arr\_lo (ulm-(llm)+1,n\_r\_max) [complex,out]

Called from step\_time()

Call to r2lm\_redist()

subroutine communications/lm2lo\_redist (arr\_lmloc, arr\_lo)

#### **Parameters**

- arr\_lmloc (ulm-(llm)+1,n\_r\_max) [complex,in]
- **arr\_lo** (ulm-(llm)+1,n\_r\_max) [complex,out]

subroutine communications/lo21m\_redist (arr\_lo, arr\_lmloc)

# **Parameters**

- arr\_lo (ulm-(llm)+1,n\_r\_max) [complex,in]
- arr\_lmloc (ulm-(llm)+1,n\_r\_max) [complex,out]

subroutine communications/myallgather(arr, dim1, dim2)

## **Parameters**

- arr (dim1,dim2) [complex,inout]
- dim1 [integer,in,]
- dim2 [integer,in,]

Use parallel\_mod, blocking

Called from dtbrms(), dtvrms()

# 10.4 Code initialization

## 10.4.1 Namelists.f90

# **Description**

Read and print the input namelist

## **Quick access**

**Routines** defaultnamelists(), writenamelists(), readnamelists()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters: Module containing the physical parameters
- init fields
- output\_data: This module contains the parameters for output control
- constants: module containing constants and parameters used in the code.
- radial\_functions
- bext: Module containing the external field parameters
- torsional oscillations: This module contains information for TO calculation and output
- truncation: This module defines the grid points and the truncation
- parallel\_mod: This module contains the blocking information
- grenoble: This module contains all variables for the case of an imposed IC dipole
- blocking (cacheblock\_size\_in\_b()): Module containing blocking information
- movie\_data(n\_movies\_max(), n\_movies(), movie())
- logic: Module containing the logicals that control the run
- num\_param: Module containing numerical and control parameters
- charmanip (length\_to\_blank(), capitalize()): This module contains several useful routines to manipule character strings

## **Variables**

# Subroutines and functions

```
subroutine namelists/readnamelists()
```

Purpose of this subroutine is to read the input namelists. This program also determins logical parameters that are stored in logic.f90.

```
Called from magic
```

```
Call to defaultnamelists(), length_to_blank(), capitalize(),
   initialize_truncation()
```

subroutine namelists/writenamelists(n\_out)

Purpose of this subroutine is to write the namelist to file unit n\_out. This file has to be open before calling this routine.

```
Parameters n_out [integer,in]
```

Called from magic

Call to length\_to\_blank()

# subroutine namelists/defaultnamelists()

Purpose of this subroutine is to set default parameters for the namelists.

Called from readnamelists()

# 10.4.2 startFiels.f90

### **Quick access**

Routines getstartfields()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (n\_r\_lcr(), kbotv(), epss(), lffac(), imagcon(), interior\_model(), ktopv(), imps()): Module containing the physical parameters
- init\_fields(init\_s1(), l\_start\_file(), initb(), inits(), init\_b1(), start\_file(), tops(), initv(), s\_cond())
- radial\_der (get\_dr(), get\_ddr()): Radial derivatives functions
- logic (l\_mag\_kin(), l\_srma(), l\_cond\_ic(), l\_conv(), l\_rot\_ma(), l\_rot\_ic(), l\_lcr(), l\_mag(), l\_sric(), l\_zl0mat(), l\_mag\_lf(), l\_heat()): Module containing the logicals that control the run
- radial\_functions (drx(), topcond(), r(), d\_costf2\_ic\_init(), i\_costf\_init(), d\_costf1\_ic\_init(), i\_costf1\_ic\_init(), dr\_fac\_ic(), botcond(), or1(), d\_costf\_init(), i\_costf2\_ic\_init(), dtemp0(), ddrx())
- blocking (nlmbs(), lmstartb(), lo\_map(), lmstopb()): Module containing blocking information
- useful (cc2real (), logwrite ()): library with several useful subroutines
- fields: This module contains the potential fields and their radial derivatives
- radial\_data(n\_r\_icb(), n\_r\_cmb())
- truncation: This module defines the grid points and the truncation
- communications (lo2r\_b(), lo2r\_w(), lo2r\_p(), get\_global\_sum(), lo2r\_redist\_start(), lo2r\_s(), lo2r\_aj(), lo2r\_z(), scatter\_from\_rank0\_to\_lo())
- parallel\_mod(n\_procs(), nlmbs\_per\_rank(), rank()): This module contains the blocking information
- grenoble (lgrenoble ()): This module contains all variables for the case of an imposed IC dipole
- fieldslast: This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- constants (two(), c\_lorentz\_ma(), one(), osq4pi(), c\_lorentz\_ic(), zero()): module containing constants and parameters used in the code.
- mpi
- lmloop\_data(ulm(), lm\_per\_rank(), llmmag(), ulmmag(), llm(), lm\_on\_last\_rank())
- num\_param (dtmax(), alpha()): Module containing numerical and control parameters
- radial der even(get ddr even())
- readcheckpoints (readstartfields ()): This module contains the functions that can help reading and mapping of the restart files

#### **Subroutines and functions**

**subroutine** start\_fields/**getstartfields**(*time*, *dt*, *dtnew*, *n\_time\_step*)

Purpose of this subroutine is to initialize the fields and other auxiliary parameters.

#### **Parameters**

- time [real,out]
- **dt** [real,out]
- dtnew [real,out]
- **n\_time\_step** [integer,out]

## Called from magic

## 10.4.3 init\_fields.f90

#### Quick access

Variables n\_s\_bounds, start\_file, s\_top, bots, tops, s\_bot, amp\_s2, omega\_ma1, omega\_ic2, bpeakbot, omegaosz\_ic1, scale\_b, tshift\_ic1, amp\_s1, omega\_ma2, bpeaktop, omegaosz\_ma2, scale\_v, tshift\_ic2, omega\_ic1, amp\_b1, tshift\_ma2, tomega\_ic1, tomega\_ma1, tomega\_ma2, omegaosz\_ic2, omegaosz\_ma1, scale\_s, tshift\_ma1, tipdipole, tomega\_ic2, amp\_v1, init\_b1, init\_s1, init\_v1, l\_reset\_t, nrotic, nrotma, inform, l\_start\_file, init\_s2, n\_start\_file

Routines initialize\_init\_fields(), inits(), j\_cond(), initb(), initv(),
 s cond()

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters(phis(), radratio(), sigma\_ratio(), widths(), kbots(), epsc(), o\_sr(), opm(), opr(), imagcon(), peaks(), thetas(), n\_imps\_max(), n\_imps(), imps(), ktops()): Module containing the physical parameters
- horizontal\_data(d\_lp1(), dlh(), hdif\_b()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_cond\_ic(), l\_rot\_ic(), l\_srma(), l\_rot\_ma(), l\_sric(), l\_anelastic\_liquid()): Module containing the logicals that control the run
- radial\_functions (jvarcon(), d2cheb(), d\_costf1\_ic\_init(), kappa(), r\_cmb(), dcheb(), cheb(), r\_icb(), i\_costf1\_ic\_init(), cheb\_ic(), d\_costf\_init(), dllambda(), d2cheb\_ic(), dtemp0(), beta(), dlkappa(), r\_ic(), dcheb\_ic(),

```
or3(), cheb\_norm(), or2(), or1(), orho1(), epscprof(), cheb\_norm\_ic(), r(), i\_costf\_init(), otemp1(), lambda())
```

- blocking (sizethetab(), st\_map(), nthetabs(), nfs(), lmp2lmps()): Module containing blocking information
- fft\_jw: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- legendre\_grid\_to\_spec(legtf1())
- radial\_data(n\_r\_icb(), n\_r\_cmb())
- truncation: This module defines the grid points and the truncation
- algebra (sgefa(), cgesl(), sgesl())
- useful (random()): library with several useful subroutines
- cosine\_transform(costf1())
- matrices (s0pivot(), jpivot(), s0mat(), jmat()): This module contains matrices for internal time step
- constants (three(), third(), two(), osq4pi(), half(), four(), c\_z10\_omega\_ic(), zero(), y10\_norm(), pi(), one(), c\_z10\_omega\_ma()): module containing constants and parameters used in the code.
- lmloop\_data(ulm(), llm(), llmmag(), ulmmag())

- init\_fields/omega\_ic2 [real,public]
- init\_fields/bpeaktop[real,public]
- init fields/init v1 [integer, public]
- init\_fields/tomega\_ma1 [real,public]
- init\_fields/omegaosz\_ic1 [real,public]
- init\_fields/tomega\_ma2 [real,public]
- init\_fields/bots(:,:) [complex,allocatable/public]
- init\_fields/l\_reset\_t [logical,public] reset time from startfile?
- init\_fields/omega\_ma1 [real,public]
- init\_fields/init\_s2 [integer,public]
- init\_fields/init\_b1 [integer, public]
- init\_fields/amp\_s1 [real, public]
- init\_fields/tshift\_ma2 [real,public]
- init\_fields/scale\_s [real, public]
- init\_fields/tshift\_ma1 [real,public]
- init\_fields/**n\_start\_file** [integer,public] I/O unit of start\_file
- init fields/n s bounds [integer,parameter=20/public]

- init\_fields/tops (:,:) [complex,allocatable/public]
- init\_fields/scale\_b [real, public]
- init\_fields/nrotic[integer,public]
- init\_fields/tipdipole [real,public] adding to symetric field
- init\_fields/bpeakbot [real,public]
- init\_fields/omegaosz\_ic2 [real,public]
- init\_fields/tshift\_ic2 [real,public]
- init\_fields/**1\_start\_file** [logical,public] taking fields from startfile ?
- init\_fields/inform[integer,public] format of start\_file
- init\_fields/amp\_s2 [real,public]
- init\_fields/omegaosz\_ma1 [real,public]
- init\_fields/tomega\_ic1 [real,public]
- init\_fields/omega\_ma2 [real,public]
- init\_fields/**start\_file** [character,public] name of start file
- init\_fields/scale\_v [real, public]
- init\_fields/nrotma[integer,public]
- init\_fields/init\_s1 [integer,public]
- init\_fields/omegaosz\_ma2 [real,public]
- init\_fields/amp\_b1 [real,public]
- init\_fields/amp\_v1 [real,public]
- init\_fields/s\_bot (80) [real,public] input variables for tops,bots
- init\_fields/tshift\_ic1 [real,public]
- init\_fields/omega\_ic1 [real,public]
- init fields/tomega ic2 [real, public]
- init\_fields/s\_top(80)[real,public]

## **Subroutines and functions**

Purpose of this subroutine is to initialize the velocity field So far it is only rudimentary and will be expanded later. Because s is needed for dwdt init\_s has to be called before.

## **Parameters**

```
• w (lm_max,n_r_max) [complex,inout]
```

- **z** (lm\_max,n\_r\_max) [complex,inout]
- omega\_ic [real,out]
- omega ma [real,out]
- **Imstart** [integer,in]
- **lmstop** [integer,in]

Called from getstartfields()

Call to fft\_thetab(), legtf1(), random()

subroutine init\_fields/inits(s, lmstart, lmstop)

Purpose of this subroutine is to initialize the entropy field according to the input control parameters.

Input	value
init_s1	random noise initialized the noise spectrum decays as 1 ^ (init_s1-1) with peak
< 100:	amplitude amp_s1 for l=1
init_s1	a specific harmonic mode initialized with amplitude amp_s1. init_s1 is interpreted as
>=100:	number llmm where ll: harmonic degree, mm: harmonic order.
init_s2	a second harmonic mode initialized with amplitude amp_s2. init_s2 is again
>100:	interpreted as number llmm where ll: harmonic degree, mm: harmonic order.

## **Parameters**

- **s** (*lm\_max*,*n\_r\_max*) [*complex*,*inout*]
- **Imstart** [integer,in]
- **lmstop** [integer,in]

Called from getstartfields()

Call to s\_cond(), random(), fft\_thetab(), legtf1(), sqefa(), sqes1()

subroutine init\_fields/initb(b, aj, b\_ic, aj\_ic, lorentz\_torque\_ic, lorentz\_torque\_ma, lmstart, lmstop)

#### **Parameters**

- **b** (lm\_maxmag,n\_r\_maxmag) [complex,inout]
- **aj** (lm\_maxmag,n\_r\_maxmag) [complex,inout]
- **b\_ic** (lm\_maxmag,n\_r\_ic\_max) [complex,inout]
- aj\_ic (lm\_maxmag,n\_r\_ic\_max) [complex,inout]
- lorentz\_torque\_ic [real,out]
- lorentz\_torque\_ma [real,out]
- **Imstart** [integer,in]
- **lmstop** [integer,in]

Called from getstartfields()

Call to j cond(), random()

```
subroutine init_fields/j_cond(lm0, aj0, aj0\_ic)
```

Purpose of this subroutine is to solve the diffusion equation for an initial toroidal magnetic field.

## **Parameters**

- lm0 [integer,in]
- **aj0** (\*) [complex,out]
- **aj0\_ic** (\*) [complex,out]

```
Called from initb()
```

```
Call to sgefa(), cgesl()
```

```
subroutine init_fields/s_cond(s0)
```

Purpose of this subroutine is to solve the entropy equation for an the conductive (l=0,m=0)-mode. Output is the radial dependence of the solution in s0.

```
Parameters s0 (*) [real,out]
Called from getstartfields(), inits()
Call to sgefa(), sgesl()
```

## 10.5 Pre-calculations

## 10.5.1 preCalc.f90

## **Quick access**

```
Routines get_hit_times(), precalctimes(), writeinfo(), precalc()
```

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (n\_r\_lcr(), o\_sr(), sigma\_ratio(), rho\_ratio\_ic(), corfac(), ra(), mode(), rho\_ratio\_ma(), ekscaled(), pr(), nvardiff(), ek(), tmagcon(), nvarvisc(), epsc0(), nvarcond(), radratio(), prmag(), epsc(), nvareps(), opm(), rascaled(), ktops(), polind(), lffac(), r\_lcr(), kbots(), interior\_model(), opr(), buofac()): Module containing the physical parameters
- init\_fields(s\_bot(), l\_reset\_t(), bots(), s\_top(), n\_s\_bounds(), tops())
- output\_data: This module contains the parameters for output control
- constants: module containing constants and parameters used in the code.
- radial\_functions (drx(), kappa(), r\_cmb(), dbeta(), d\_costf\_init(), divktemp0(), radial(), rgrav(), visc(), dlvisc(), temp0(), r\_icb(), dentropy0(), dllambda(), beta(), dlkappa(), r\_surface(), i\_costf\_init(), transportproperties(), sigma(), ddrx(), dddrx(), r(), rhoo(), lambda())
- bext (l\_curr(), fac\_loop()): Module containing the external field parameters
- useful (logwrite()): library with several useful subroutines

10.5. Pre-calculations 181

- truncation(n\_phi\_max(), lm\_max(), n\_r\_max(), n\_cheb\_max(), minc(), n\_theta\_max(), m\_max(), n\_cheb\_ic\_max(), l\_max(), nalias(), n\_r\_ic\_max()): This module defines the grid points and the truncation
- integration (rint\_r()): Radial integration functions
- parallel\_mod (rank ()): This module contains the blocking information
- horizontal\_data (horizontal()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_storepot(), l\_newmap(), l\_storebpot(), l\_non\_rot(), l\_cmb\_field(), l\_cond\_ic(), l\_dt\_cmb\_field(), l\_storetpot(), l\_storevpot(), l\_time\_hits(), l\_r\_field(), l\_tomovie(), l\_to(), l\_anel(), l\_lcr(), l\_mag(), l\_save\_out(), l\_anelastic\_liquid(), l\_mag\_lf(), l\_heat(), l\_movie()): Module containing the logicals that control the run
- num\_param: Module containing numerical and control parameters

#### Subroutines and functions

```
subroutine precalculations/precalc()
```

Purpose of this subroutine is to initialize the calc values, arrays, constants that are used all over the code. The stuff is stored in the common blocks. MPI: This is called by every processors.

```
Called from magic
```

```
Call to radial(), transportproperties(), horizontal(), rint_r(),
logwrite()
```

subroutine precalculations/precalctimes (time, n time step)

Precalc. after time, time and dthas been read from startfile.

## **Parameters**

- time [real,out]
- n\_time\_step [integer,out]

Called from magic

Call to get\_hit\_times()

## **Parameters**

- $t (n_t_max) [real,inout] :: Times for output$
- n\_t\_max [integer,in,] :: Dimension of t(\*)
- **n\_t** [integer,out] :: No. of output times
- **l\_t** [logical,out] :: =.true. if output times are defined
- t\_start [real,inout] :: Starting time for output
- t stop [real,inout] :: Stop time for output

- **dt** [real,inout] :: Time step for output
- **n\_tot** [integer,inout] :: No. of output (times) if no times defined
- n\_step [integer,inout] :: Ouput step in no. of time steps
- **string\_bn** [character,in]
- **time** [real,in] :: Time of start file
- tscale [real,in]

Called from precalctimes()

subroutine precalculations/writeinfo(n\_out)

Purpose of this subroutine is to write the namelist to file unit n\_out. This file has to be open before calling this routine.

Parameters n\_out [integer,in]

Called from magic

## 10.5.2 radial.f90

#### **Quick access**

Variables d\_costf2\_ic\_init, orho1, divktemp0, agrav, dlkappa, otemp1, temp0, or2, visc, d2cheb, dtemp0, orho2, d\_costf\_init, cheb, dllambda, r, or4, cheb\_ic, cheb\_int\_ic, d3cheb, sigma, or3, dlvisc, rho0, jvarcon, dentropy0, d\_costf\_initc, r\_ic, kappa, epscprof, d2temp0, dbeta, dddrx, rgrav, rc, dcheb, drx, dcheb\_ic, o\_r\_ic, ddrx, or1, lambda, beta, dr\_facc, d\_costf1\_ic\_init, o\_r\_ic2, d2cheb\_ic, cheb\_int, i\_costf2\_ic\_init, i\_costf1\_ic\_init, i\_costf\_initc, i\_costf\_init, botcond, r\_surface, topcond, alpha2, alpha1, r\_cmb, alph2, dr\_fac, alph1, r\_icb, cheb\_norm\_ic, dr\_fac\_ic, cheb\_norm, ndi\_costf1, ndd\_costf1, n\_cheb\_maxc, ncut, n\_r\_maxc, ndi\_costf2\_ic, ndd\_costf2\_ic, ndd\_costf1\_ic, ndi\_costf1\_ic

```
Routines radial(), transportproperties(), getbackground(), initialize_radial_functions()
```

## Needed modules

- physical\_parameters: Module containing the physical parameters
- chebyshev\_polynoms\_mod
- radial\_der(get\_dr()): Radial derivatives functions
- constants (three(), two(), one(), half(), four(), sq4pi()): module containing constants and parameters used in the code.
- init\_costf
- cosine\_transform(costf1())
- matrices (s0pivot(), s0mat()): This module contains matrices for internal time step
- logic (l\_newmap(), l\_anel(), l\_cond\_ic(), l\_isothermal(), l\_mag(), l\_anelastic\_liquid(), l\_heat()): Module containing the logicals that control the run

10.5. Pre-calculations 183

- num\_param (alpha ()): Module containing numerical and control parameters
- truncation (n\_r\_max(), n\_cheb\_max(), n\_r\_ic\_max()): This module defines the grid points and the truncation
- algebra (sgefa(), sgesl())

- radial\_functions/jvarcon(:) [real,allocatable/public]
- radial\_functions/or4(:)[real,allocatable/public]
- radial\_functions/ $\mathbf{r}$ \_ $\mathbf{cmb}$  [real,public]

OC radius

- radial\_functions/alph2 [real,public]
  Input parameter for non-linear map to define central point of different spacing (-1.0:1.0)
- radial\_functions/botcond[real,public]
  Heat flux at IC boundary
- radial\_functions/r\_icb [real,public]
   IC radius
- radial\_functions/**visc**(:) [real,allocatable/public]
- radial\_functions/d\_costf2\_ic\_init(:) [real,allocatable/public]
- radial\_functions/topcond [real,public]
  Heat flux at OC boundary
- radial\_functions/dcheb\_ic(:,:) [real,allocatable/public]
- radial\_functions/rho0 (:) [real,allocatable/public]
- radial\_functions/orho1 (:) [real,allocatable/public]
- radial\_functions/cheb\_int\_ic(:) [real,allocatable/public]
- radial\_functions/**beta**(:)[real,allocatable/public]
- radial\_functions/**dddrx**(:) [real,allocatable/public]
- radial\_functions/ndd\_costf1 [integer,public]
   Radii for transform
- radial\_functions/**dr\_facc**(:) [real,allocatable/public]
- radial\_functions/ndi\_costf2\_ic [integer,public]
   Radii for transform
- radial\_functions/**cheb\_norm\_ic** [real,public]
  Chebyshev normalisation for IC
- radial\_functions/d\_costf1\_ic\_init(:) [real,allocatable/public]
- radial\_functions/rgrav(:) [real,allocatable/public]
- radial\_functions/ncut [integer,public]

Truncation

- radial\_functions/o\_r\_ic(:) [real, allocatable/public]
- radial\_functions/d\_costf\_init(:)[real,allocatable/public]

```
• radial_functions/ddrx(:)[real,allocatable/public]
```

- radial\_functions/d2temp0 (:) [real,allocatable/public]
- radial\_functions/r\_ic(:) [real,allocatable/public]
- radial\_functions/d3cheb (:,:) [real,allocatable/public]
- radial\_functions/**dlkappa** (:) [real,allocatable/public]
- radial\_functions/ndi\_costfl\_ic [integer,public]
   Radii for transform
- radial\_functions/alph1 [real,public]
  Input parameter for non-linear map to define degree of spacing (0.0:2.0)
- radial\_functions/rc(:) [real,allocatable/public]
- radial\_functions/cheb\_ic(:,:) [real,allocatable/public]
- radial\_functions/d\_costf\_initc(:) [real,allocatable/public]
- radial\_functions/or1 (:) [real, allocatable/public]
- radial\_functions/lambda(:)[real,allocatable/public]
- radial\_functions/ndi\_costf1 [integer,public]
   Radii for transform
- radial\_functions/orho2 (:) [real,allocatable/public]
- radial\_functions/alpha2 [real,public]
  Input parameter for non-linear map to define central point of different spacing (-1.0:1.0)
- radial\_functions/n\_r\_maxc [integer,public]
   Number of radial points
- radial\_functions/i\_costfl\_ic\_init(:)[integer,allocatable/public]
- radial\_functions/drx (:) [real, allocatable/public]
- radial\_functions/i\_costf\_initc(:) [integer, allocatable/public]
- radial\_functions/temp0 (:) [real,allocatable/public]
- radial\_functions/ndd\_costf2\_ic [integer,public]
  Radii for transform
- radial\_functions/epscprof(:) [real,allocatable/public]
- radial\_functions/**r\_surface** [real,public]
  Surface radius for extrapolation
- radial\_functions/or3(:) [real,allocatable/public]
- radial\_functions/or2 (:) [real,allocatable/public]
- radial\_functions/ndd\_costf1\_ic [integer,public]
  Radii for transform
- radial\_functions/dcheb(:,:) [real,allocatable/public]
- radial\_functions/alpha1 [real,public]
  Input parameter for non-linear map to define degree of spacing (0.0:2.0)
- radial\_functions/otemp1 (:) [real,allocatable/public]
- radial\_functions/**d2cheb** (:,:) [real,allocatable/public]

10.5. Pre-calculations 185

```
• radial_functions/kappa (:) [real, allocatable/public]
   • radial_functions/dbeta(:) [real,allocatable/public]
   • radial_functions/dr_fac [real,public]
         2./d, where d=r cmb-r icb
   • radial functions/cheb (:,:) [real, allocatable/public]
   • radial_functions/o_r_ic2 (:) [real,allocatable/public]
   • radial_functions/divktemp0 (:) [real,allocatable/public]
   • radial_functions/n_cheb_maxc[integer,public]
         Number of Chebyshevs
   • radial_functions/dentropy0(:) [real, allocatable/public]
   • radial_functions/dllambda (:) [real,allocatable/public]
   • radial_functions/d2cheb_ic(:,:) [real,allocatable/public]
   • radial_functions/dtemp0 (:) [real,allocatable/public]
   radial_functions/cheb_norm[real,public]
         Chebyshev normalisation
   • radial_functions/cheb_int(:)[real,allocatable/public]
   • radial functions/r(:) [real, allocatable/public]
   • radial_functions/i_costf_init(:)[integer,allocatable/public]
   • radial_functions/dlvisc(:) [real,allocatable/public]
   • radial_functions/dr_fac_ic[real,public]
         For IC: two/(two*r_icb)
   • radial_functions/sigma (:) [real,allocatable/public]
   • radial_functions/i_costf2_ic_init(:) [integer,allocatable/public]
   • radial_functions/agrav(:) [real,allocatable/public]
Subroutines and functions
subroutine radial_functions/initialize_radial_functions()
         Called from magic
subroutine radial_functions/radial()
     Calculates everything needed for radial functions, transfroms etc.
         Called from precalc()
         Call to cheb_grid(), init_costf1(), getbackground(), get_chebs_even(),
             init_costf2()
subroutine radial_functions/transportproperties()
     Calculates the transport properties: electrical conductivity, kinematic viscosity and thermal conductivity.
         Called from precalc()
```

**subroutine** radial\_functions/**getbackground** (*input*, *boundaryval*, *output*)

Linear solver of the form: df/dx = input with f(1)=boundaryVal

## **Parameters**

```
• input (n_r_max) [real,in]
```

- boundaryval [real,in]
- **output** (*n\_r\_max*) [real,out]

Called from radial()

Call to sgefa(), sgesl()

## 10.5.3 horizontal.f90

## **Description**

Module containing functions depending on longitude and latitude plus help arrays depending on degree and order

## **Quick access**

Variables dphi0, dtheta4s, d\_mc2m, hdif\_v, plm, sintheta, o\_sin\_theta, wplm, hdif\_b, d\_1, d\_m, dphi02, costheta, cosn2, phi, dplm, gauss, dtheta2a, sn2, dlh, osn2, dtheta2s, osn1, theta, dtheta3s, dphi, d\_1p1, o\_sin\_theta\_e2, hdif\_s, dtheta4a, dtheta3a, dtheta1s, dtheta1a, dpl0eq, theta\_ord, lmodd, lstop, lstartp, lstart, lstopp, n\_theta\_cal2ord, lmoddp

**Routines** initialize\_horizontal\_data(), horizontal(), gauleg()

## **Needed modules**

- physical\_parameters (ek ()): Module containing the physical parameters
- precision\_mod: This module controls the precision used in MagIC
- logic(l\_non\_rot()): Module containing the logicals that control the run
- radial functions(r cmb())
- blocking (1m2m (), 1mp21 (), 1mp21 (), 1mp21m ()): Module containing blocking information
- fft\_jw (init\_fft ()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- constants (one (), half (), zero (), two (), pi ()): module containing constants and parameters used in the code.
- num\_param (difeta(), difkap(), difnu(), ldifexp(), ldif()): Module containing numerical and control parameters
- truncation (n\_phi\_max(), lm\_max(), minc(), n\_theta\_max(), m\_max(), l\_max(), n\_m\_max(), lmp\_max()): This module defines the grid points and the truncation
- plms\_theta(plm\_thetaas(), plm\_theta())

10.5. Pre-calculations 187

- horizontal\_data/lstartp(:) [integer,allocatable/public]
- horizontal\_data/costheta(:)[real,allocatable/public]
- horizontal\_data/dphi0 (:) [complex,allocatable/public]
- horizontal\_data/dtheta2s(:)[real,allocatable/public]
- horizontal\_data/dlh(:) [real,allocatable/public]
- horizontal\_data/osn2 (:) [real,allocatable/public]
- horizontal\_data/plm(:,:) [real,allocatable/public]
- horizontal\_data/gauss(:)[real,allocatable/public]
- horizontal\_data/dpl0eq(:) [real,allocatable/public]
- horizontal\_data/lstart (:) [integer,allocatable/public]
- horizontal\_data/dtheta2a(:)[real,allocatable/public]
- horizontal\_data/dtheta4s(:)[real,allocatable/public]
- horizontal\_data/cosn2 (:) [real, allocatable/public]
- horizontal\_data/lstopp(:)[integer,allocatable/public]
- horizontal\_data/hdif\_s (:) [real,allocatable/public]
- horizontal\_data/dthetala(:)[real,allocatable/public]
- horizontal\_data/lmodd(:)[logical,allocatable/public]
- horizontal\_data/sintheta(:)[real,allocatable/public]
- horizontal\_data/d\_lp1 (:) [real,allocatable/public]
- horizontal\_data/d\_1(:) [real,allocatable/public]
- horizontal\_data/o\_sin\_theta\_e2 (:) [real,allocatable/public]
- horizontal\_data/sn2(:)[real,allocatable/public]
- horizontal\_data/o\_sin\_theta(:)[real,allocatable/public]
- horizontal\_data/**phi** (:) [real,allocatable/public]
- horizontal\_data/lmoddp (:) [logical,allocatable/public]
- horizontal\_data/wplm(:,:) [real,allocatable/public]
- $\bullet \ \texttt{horizontal\_data/dtheta4a} \ (:) \ \textit{[real,allocatable/public]}$
- horizontal\_data/theta(:)[real,allocatable/public]
- horizontal\_data/dtheta3a(:)[real,allocatable/public]
- horizontal\_data/n\_theta\_cal2ord(:) [integer,allocatable/public]
- horizontal\_data/lstop(:)[integer,allocatable/public]
- horizontal\_data/hdif\_v(:) [real,allocatable/public]
- horizontal\_data/dtheta3s(:)[real,allocatable/public]
- horizontal\_data/dphi(:)[complex,allocatable/public]
- horizontal\_data/theta\_ord(:) [real,allocatable/public]

- horizontal\_data/osn1 (:) [real,allocatable/public]
- horizontal\_data/hdif\_b (:) [real,allocatable/public]
- horizontal\_data/d\_m(:) [real,allocatable/public]
- horizontal\_data/dplm(:,:) [real,allocatable/public]
- horizontal\_data/dphi02 (:) [complex,allocatable/public]
- horizontal\_data/d\_mc2m(:) [real,allocatable/public]
- horizontal\_data/dtheta1s(:)[real,allocatable/public]

## Subroutines and functions

```
subroutine horizontal_data/initialize_horizontal_data()
```

Called from magic

```
subroutine horizontal_data/horizontal()
```

Calculates functions of theta and phi, for exmample the Legendre functions, and functions of degree l and order m of the legendres.

```
Called from precalc()
```

```
Call to gauleg(), plm_theta(), plm_thetaas(), init_fft()
```

**subroutine** horizontal\_data/**gauleg** (sinthmin, sinthmax, theta\_ord, gauss, n\_th\_max)

Subroutine is based on a NR code. Calculates N zeros of legendre polynomial P(l=N) in the interval [sinThMin,sinThMax]. Zeros are returned in radiants theta\_ord(i) The respective weights for Gauss-integration are given in gauss(i).

#### **Parameters**

- **sinthmin** [real,in] :: lower bound in radiants
- **sinthmax** [real,in] :: upper bound in radiants
- **theta\_ord** (n\_th\_max) [real,out] :: zeros cos(theta)
- gauss (n\_th\_max) [real,out] :: associated Gauss-Legendre weights
- **n** th max [integer,in] :: desired maximum degree

Called from horizontal ()

# 10.6 Time stepping

## 10.6.1 step\_time.f90

## **Quick access**

```
Variables dwdt_lmloc, dzdt_lmloc, dpdt_lmloc, dbdt_lmloc, dvxbhlm_rloc, djdt_rloc, dpdt_rloc, dsdt_lmloc, djdt_lmloc, dbdt_rloc, dwdt_rloc, dvxbhlm_lmloc, dsdt_rloc, dvsrlm_rloc, dzdt_rloc, dvsrlm_lmloc
```

**Routines** check\_time\_hits(), step\_time(), initialize\_step\_time()

- output\_data (n\_to\_step(), t\_r\_field(), n\_rst\_step(), t\_tpot(), graph\_file(),
   t\_graph(), n\_t\_r\_field(), n\_time\_hits(), tag(), n\_tomovie\_frames(),
   n\_vpot\_step(), n\_t\_movie(), n\_stores(), log\_file(), n\_log\_step(),
   n\_graph\_step(), n\_tozs(), n\_log\_file(), n\_t\_toz(), n\_bpots(), n\_tpot\_step(),
   n\_t\_tpot(), t\_rst(), t\_bpot(), n\_t\_tomovie(), t\_vpot(), n\_t\_spec(), t\_tomovie(),
   n\_bpot\_step(), n\_t\_log(), n\_r\_fields(), n\_t\_bpot(), n\_tos(), n\_cmbs(),
   n\_tomovie\_step(), n\_cmb\_step(), l\_graph\_time(), n\_toz\_step(), t\_to(), n\_t\_rst(),
   graph\_mpi\_fh(), n\_movie\_step(), n\_t\_graph(), t\_toz(), n\_r\_field\_step(),
   t\_cmb(), n\_t\_cmb(), n\_vpots(), n\_t\_to(), nlf(), t\_spec(), n\_logs(), n\_t\_vpot(),
   t\_log(), n\_specs(), n\_tpots(), t\_movie(), n\_rsts(), n\_spec\_step(), n\_graphs(),
   n\_movie\_frames()): This module contains the parameters for output control
- constants (one (), half (), zero ()): module containing constants and parameters used in the code.
- blocking (lmstartb(), nlmbs(), lmstopb()): Module containing blocking information
- useful (safeopen(), l\_correct\_step(), safeclose(), logwrite()): library with several useful subroutines
- fields: This module contains the potential fields and their radial derivatives
- movie\_data(t\_movies())
- truncation (l\_maxmag(), lm\_max(), n\_r\_max(), lm\_maxmag(), l\_max(), n\_r\_maxmag(), lmp\_max()): This module defines the grid points and the truncation
- parallel\_mod: This module contains the blocking information
- output\_mod(output())
- Imloop mod (Imloop())
- timing: Useful functions for time-stepping
- precision\_mod: This module controls the precision used in MagIC
- radialloop(radialloopg())
- logic (l\_storebpot(), l\_cmb\_field(), l\_conv(), l\_save\_out(), l\_hel(), l\_storevpot(), l\_tomovie(), l\_to(), l\_dtbmovie(), l\_ht(), l\_dtb(), l\_dtrmagspec(), l\_rms(), l\_mag\_lf(), l\_true\_time(), l\_perppar(), lverbose(), l\_b\_nl\_cmb(), l\_storetpot(), l\_fluxprofs(), l\_time\_hits(), l\_r\_field(), l\_runtimelimit(), l\_htmovie(), l\_mag(), l\_b\_nl\_icb(), l\_viscbccalc(), l\_heat(), l\_movie()): Module containing the logicals that control the run
- radial\_data  $(n_r_icb(), n_r_cmb(), nrstart(), nrstop(), nrstopmag(), nrstartmag())$
- communications (lm2r\_type(), lo2r\_b(), lo2r\_aj(), lo2r\_w(), lo2r\_p(), lo2r\_s(), lo2r\_redist\_start(), get\_global\_sum(), r2lo\_redist(), lo2r\_z(), lo2r\_redist\_wait())
- charmanip (dble2str(), capitalize()): This module contains several useful routines to manipule character strings
- courant\_mod(dt\_courant())
- fieldslast: This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.

- num\_param (runtime(), n\_time\_steps(), dtmax(), dtmin(), tscale(), runtimelimit(), tend(), alpha()): Module containing numerical and control parameters
- lmloop\_data(ulm(), lm\_per\_rank(), llmmag(), ulmmag(), llm(), lm\_on\_last\_rank())
- nonlinear\_bcs(get\_b\_nl\_bcs())

- step\_time\_mod/dbdt\_rloc(:,:) [complex,private/target/allocatable]
- step\_time\_mod/**dbdt\_lmloc** (:,:) [complex,private/allocatable]
- step\_time\_mod/**dsdt\_rloc**(:,:) [complex,private/allocatable]
- step\_time\_mod/dvxbhlm\_lmloc(:,:) [complex,private/allocatable]
- step\_time\_mod/dvxbhlm\_rloc(:,:) [complex,private/allocatable]
- $\bullet \ \, \mathtt{step\_time\_mod/dsdt\_lmloc} \, (:,:) \, [\mathit{complex,private/allocatable}] \\$
- step\_time\_mod/dzdt\_rloc(:,:) [complex,private/allocatable]
- step\_time\_mod/dvsrlm\_rloc(:,:) [complex,private/allocatable]
- step\_time\_mod/**dvsrlm\_lmloc**(:,:) [complex,private/allocatable]
- step\_time\_mod/**djdt\_rloc**(:,:) [complex,private/allocatable]
- step\_time\_mod/**dpdt\_rloc** (:,:) [complex,private/allocatable]
- step\_time\_mod/djdt\_lmloc(:,:) [complex,private/allocatable]
- step\_time\_mod/**dwdt\_rloc**(:,:) [complex,private/allocatable]
- $\bullet \ \, \mathtt{step\_time\_mod/dpdt\_lmloc} \, (:,\!:) \, [\mathit{complex,private/allocatable}] \\$
- step\_time\_mod/dwdt\_lmloc(:,:) [complex,private/allocatable]
- step\_time\_mod/dzdt\_lmloc(:,:) [complex,private/allocatable]

## **Subroutines and functions**

```
subroutine step_time_mod/initialize_step_time()
```

Called from magic

subroutine step\_time\_mod/step\_time (time, dt, dtnew, n\_time\_step)

This subroutine performs the actual time-stepping.

## **Parameters**

- time [real,inout]
- **dt** [real,inout]
- **dtnew** [real,inout]
- **n\_time\_step** [integer,inout]

Called from magic

```
Call to walltime(), lo2r_redist_wait(), capitalize(), time2ms(),
    ms2time(), ltimelimit(), logwrite(), l_correct_step(), dble2str(),
    safeopen(), safeclose(), radialloopg(), lnegtime(), subtime(),
    addtime(), r2lo_redist(), output(), get_b_nl_bcs(), dt_courant(),
    check_time_hits(), lmloop(), meantime(), writetime()
```

subroutine step time mod/check time hits (l new dt, time, dt, dt new)

Checks whether a certain dt is required to hit a specific output-time.

## **Parameters**

- l\_new\_dt [logical,out] :: signfies change of dt !
- time [real,inout]
- **dt** [real,inout]
- dt\_new [real,inout]

Called from step time()

## 10.6.2 courant.f90

## **Quick access**

```
Routines dt_courant(), courant()
```

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (opm(), 1ffac()): Module containing the physical parameters
- horizontal\_data(osn2()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_mag(), l\_mag\_lf(), l\_mag\_kin()): Module containing the logicals that control the run
- radial\_functions(orho2(), or4(), or2(), orho1())
- blocking (nfs ()): Module containing blocking information
- useful (logwrite()): library with several useful subroutines
- radial\_data(nrstop(), nrstart())
- truncation (n\_phi\_max(), nrp()): This module defines the grid points and the truncation
- parallel\_mod: This module contains the blocking information
- constants (one (), half (), two ()): module containing constants and parameters used in the code.
- num\_param(alffac(), delxr2(), delxh2(), courfac()): Module containing numerical and control parameters

#### **Subroutines and functions**

**subroutine** courant\_mod/**courant** (*n\_r*, *dtrkc*, *dthkc*, *vr*, *vt*, *vp*, *br*, *bt*, *bp*, *n\_theta\_min*, *n\_theta\_block*)

#### **Parameters**

- **n\_r** [integer,in] :: radial level
- **dtrkc** [real,inout] :: Courant step (based on radial advection)
- dthkc [real,inout] :: Courant step based on horizontal advection
- **vr** (*nrp*,*nfs*) [real,in] :: radial velocity
- vt (nrp,nfs) [real,in] :: longitudinal velocity
- **vp** (*nrp*,*nfs*) [*real*,*in*] :: azimuthal velocity
- **br** (*nrp*,*nfs*) [*real*,*in*] :: radial magnetic field
- **bt** (*nrp*,*nfs*) [real,in] :: longitudinal magnetic field
- **bp** (nrp,nfs) [real,in] :: azimuthal magnetic field
- n\_theta\_min [integer,in] :: first theta in block stored in fields
- n\_theta\_block [integer,in] :: size of theta block

**Called from** do\_iteration\_thetablocking\_seq(), do\_iteration\_thetablocking\_openmp()

**subroutine** courant\_mod/**dt\_courant** (*dt\_r*, *dt\_h*, *l\_new\_dt*, *dt*, *dt\_new*, *dtmax*, *dtrkc*, *dthkc*)

Check if Courant criterion based on combined fluid and Alfven velocity is satisfied Returns new value of time step dtnew

dtr,dth: (output) radial/horizontal Courant time step n\_time\_step: (input) time step number l\_new\_dt: (output) flag indicating that time step is changed (=1) or not (=0) dt: (input) old time step dtnew: (output) new time step dtMin: (input) lower limit for time step (termination if dtnew < dtMin) dtMax: (input) upper limit for time step dtrkc: (input) radial Courant time step as function of radial level dthkc: (input) horizontal Courant time step as function of radial level

## Parameters

- **dt\_r** [real,out]
- dt\_h [real,out]
- l\_new\_dt [logical,out]
- **dt** [real,in]
- dt\_new [real,out]
- dtmax [real,in]
- dtrkc (nrstop-(nrstart)+1) [real,in]
- dthkc (nrstop-(nrstart)+1) [real,in]

Called from step\_time()

Call to logwrite()

## 10.6.3 timing.f90

## **Description**

Useful functions for time-stepping

## **Quick access**

```
Variables msechour, msecsecond, msecminute
Routines ltimelimit(), time2ms(), lnegtime(), walltime(), ms2time(), addtime(), writetime(), subtime()
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- mpi
- parallel\_mod (rank ()): This module contains the blocking information

## **Variables**

- timing/msecsecond [integer, private/parameter=1000]
- timing/msechour[integer,private/parameter=3600000]
- timing/msecminute[integer,private/parameter=60000]

## **Subroutines and functions**

```
subroutine timing/walltime (time)
```

This routine returns the wallclock time in four integer arguments.

```
Parameters time (4) [integer,out]
Called from step_time(), lmloop(), magic
Call to ms2time()
```

```
subroutine timing/ms2time (ms, time)
```

Transforms accumulated milliseconds ms into an four-element integer arrays time(4) containing the time in hours=time(1), minutes=time(2), seconds=time(3), and milliseconds=time(4).

## **Parameters**

- ms [integer,in]
- **time** (4) [integer,out]

```
Called from walltime(), meantime(), step time(), addtime(), subtime()
```

function timing/time2ms (time)

Transforms a four-element integer arrays time(4) containing the time in hours=time(1), minutes=time(2), seconds=time(3), and milliseconds=time(4) into accumulated milliseconds.

```
Parameters time (4) [integer,in]
          Return time2ms [integer]
          Called from meantime(), step time(), addtime(), lnegtime(), subtime()
subroutine timing/subtime (timestart, timestop, timed)
          Returns time passed between timeStop and timeStart. Note timeStop has to be younger than timeS-
          tart, otherwise 24 hours are added. This is necessary on systems like the IBM where the time counter
          as reset every day at midnight.
          Parameters
                • timestart (4) [integer,in]
                • timestop (4) [integer,in]
                • timed (4) [integer,out]
          Called from step_time(), lmloop()
          Call to time2ms(), ms2time()
function timing/ltimelimit (time, timemax)
          True when time exeeds timeMax
          Parameters
                • time (4) [integer,in]
                • timemax (4) [integer,in]
          Return Itimelimit [logical]
          Called from step_time()
subroutine timing/addtime (time1, time2)
          Parameters
                • time1 (4) [integer]
                • time2 (4) [integer]
          Called from step_time()
          Call to time2ms(), ms2time()
subroutine timing/meantime (time, n)
          Parameters
                • time (4) [integer]
                • n [integer,in]
          Called from step_time()
          Call to time2ms(), ms2time()
```

function timing/lnegtime (time1, time2)

Negative passed time? Means we have passed midnight. The wallclock time is reset to zero on some computers at midnight.

## **Parameters**

- **time1** (4) [integer,in]
- **time2** (4) [integer,in]

## **Return Inegtime** [logical]

Called from step\_time()

Call to time2ms()

subroutine timing/writetime (nout, text, time)

Returns time passed between timeStop and timeStart. Note timeStop has to be younger than timeStart, otherwise 24 hours are added. This is necessary on systems like the IBM where the time counter are reset every day at midnight.

#### **Parameters**

- nout [integer,in]
- text [character,in]
- time (4) [integer,in]

Called from step\_time(), lmloop(), magic

# 10.7 Linear calculation part of the time stepping (LMLoop)

## 10.7.1 LMLoop.f90

#### **Quick access**

Routines lmloop(), initialize\_lmloop()

- precision\_mod: This module controls the precision used in MagIC
- lmloop\_data(ulm(), llm(), llmmag(), ulmmag())
- updatewp\_mod(updatewp(), initialize\_updatewp())
- output\_data (nlf(), log\_file()): This module contains the parameters for output control
- logic (l\_mag(), l\_anelastic\_liquid(), l\_heat(), lverbose(), l\_conv()): Module containing the logicals that control the run
- debugging (debug\_write())
- omp\_lib
- blocking (lmstartb(), lmstopb()): Module containing blocking information
- useful (safeopen(), safeclose()): library with several useful subroutines

- fields: This module contains the potential fields and their radial derivatives
- radial\_data(n\_r\_icb(), n\_r\_cmb())
- truncation(lm\_max(), n\_r\_max(), l\_max(), n\_r\_maxmag()): This module defines the grid points and the truncation
- communications (lo2r\_b(), lo2r\_w(), lo2r\_p(), lo2r\_s(), lo2r\_redist\_start(), get\_global\_sum(), lo2r\_aj(), lo2r\_z())
- parallel\_mod (rank ()): This module contains the blocking information
- updates\_mod(updates\_ala(), initialize\_updates(), updates())
- updatez\_mod(initialize\_updatez(), updatez())
- fieldslast: This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- updateb\_mod(initialize\_updateb(), updateb())
- matrices (lsmat(), lbmat(), lzmat(), lwpmat(), lz10mat()): This module contains matrices for internal time step
- timing (walltime(), writetime(), subtime()): Useful functions for time-stepping

## Subroutines and functions

**subroutine** lmloop\_mod/**lmloop** (w1, coex, time, dt, lmat, lrmsnext, dvxbhlm, dvsrlm, dsdt, dwdt, dzdt, dpdt, dbdt, djdt, lorentz\_torque\_ma, lorentz\_torque\_ic, b\_nl\_cmb, aj\_nl\_icb, n\_time\_step)

This subroutine performs the actual time-stepping.

#### **Parameters**

- **w1** [real,in]
- coex [real,in]
- time [real,in]
- dt [real,in]
- lmat [logical,in]
- **lrmsnext** [logical,in]
- **dvxbhlm** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,inout]
- **dvsrlm** (*ulm*-(*llm*)+1,*n\_r\_max*) [complex,inout]
- **dsdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*inout*]
- **dwdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]

```
• dzdt (ulm-(llm)+1,n_r_max) [complex,in]
```

- **dpdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dbdt** (*ulmmag-(llmmag*)+1,*n\_r\_maxmag*) [*complex*,*in*]
- **djdt** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [*complex,inout*]
- lorentz\_torque\_ma [real,in]
- lorentz torque ic [real,in]
- **b\_nl\_cmb** (*lm\_max*) [*complex,in*] :: nonlinear bc for b at CMB
- aj\_nl\_cmb (lm\_max) [complex,in] :: nonlinear bc for aj at CMB
- aj\_nl\_icb (lm\_max) [complex,in] :: nonlinear bc for dr aj at ICB
- n\_time\_step [integer,in]

```
Called from step_time()
```

```
Call to safeopen(), walltime(), updates_ala(), updates(),
    lo2r_redist_start(), updatewp(), updateb(), subtime(), writetime(),
    safeclose()
```

## 10.7.2 updateWP.f90

#### **Quick access**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (kbotv(), ktopv(), ra()): Module containing the physical parameters
- parallel\_mod (chunksize ()): This module contains the blocking information
- horizontal\_data(hdif\_v(), dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_update\_v(), l\_rmstest()): Module containing the logicals that control the run
- radial\_functions (cheb\_norm(), drx(), or1(), dbeta(), dcheb(), cheb(), i\_costf\_init(), or2(), d2cheb(), rgrav(), agrav(), dlvisc(), d3cheb(), beta(), dddrx(), d costf init(), visc(), rho0(), ddrx())
- omp\_lib
- blocking (lmstartb(), st\_map(), st\_sub\_map(), lo\_sub\_map(), nlmbs(), lmstopb(), lo\_map()): Module containing blocking information
- cosine\_transform(costf1())
- radial\_data(n\_r\_icb(), n\_r\_cmb())
- truncation (lm\_max(), n\_r\_max(), n\_cheb\_max()): This module defines the grid points and the truncation

- algebra (cgeslml(), sgefa())
- communications (get global sum())
- rms\_helpers (hint2pol()): This module contains several useful subroutines required to compute RMS diagnostics
- radial\_der(get\_dddr(), get\_dr()): Radial derivatives functions
- matrices (wpmat\_fac(), wpmat(), wppivot(), lwpmat()): This module contains matrices for internal time step
- constants (three (), third (), two (), one (), half (), four (), zero ()): module containing constants and parameters used in the code.
- num\_param (alpha()): Module containing numerical and control parameters
- lmloop\_data(ulm(), llm())
- rms (difpolas2hint(), difpollmr(), difpollmr(), dtvpol2hint(), dtvpol2hint(), dtvpollmr()): This module contains the global array used when RMS force balance is requested

- updatewp\_mod/buo(:) [complex,private/allocatable]
- updatewp\_mod/dif(:) [complex,private/allocatable]
- updatewp\_mod/worka (:,:) [complex,private/allocatable]
- updatewp\_mod/workb (:,:) [complex,private/allocatable]
- updatewp\_mod/rhs1(:,:,:) [complex,private/allocatable]
- updatewp\_mod/**pre**(:) [complex,private/allocatable]
- updatewp\_mod/maxthreads [integer,private]

## **Subroutines and functions**

```
subroutine updatewp_mod/initialize_updatewp()
```

```
Called from initialize_lmloop()
```

subroutine updatewp\_mod/finalize\_updatewp()

**subroutine** updatewp\_mod/**updatewp** (*w*, *dw*, *ddw*, *dwdt*, *dwdtlast*, *p*, *dp*, *dpdt*, *dpdtlast*, *s*, *w1*, *coex*, *dt*, *nlmb*, *lrmsnext*)

updates the poloidal velocity potential w, the pressure p, and their derivatives adds explicit part to time derivatives of w and p

## **Parameters**

- $\mathbf{w}$  (ulm-(llm)+1,n\_r\_max) [complex,inout]
- **dw** (*ulm*-(*llm*)+1,*n\_r\_max*) [complex,inout]
- **ddw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*, *out*]
- **dwdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dwdtlast** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [complex,inout]

```
p (ulm-(llm)+1,n_r_max) [complex,inout]
dp (ulm-(llm)+1,n_r_max) [complex,out]
dpdt (ulm-(llm)+1,n_r_max) [complex,in]
dpdtlast (ulm-(llm)+1,n_r_max) [complex,inout]
s (ulm-(llm)+1,n_r_max) [complex,in]
w1 [real,in] :: weight for time step!
coex [real,in] :: factor depending on alpha
dt [real,in] :: time step
nlmb [integer,in] :: block number
lrmsnext [logical,in]

Called from lmloop()
```

subroutine updatewp\_mod/get\_wpmat (dt, l, hdif, wpmat, wppivot, wpmat\_fac)

Call to get\_wpmat(), cgeslml(), get\_dddr(), hint2pol()

Purpose of this subroutine is to contruct the time step matrix wpmat for the NS equation.

## **Parameters**

- **dt** [real,in]
- l [integer,in]
- hdif [real,in]
- wpmat (2\*n\_r\_max,2\*n\_r\_max) [real,out]
- wppivot (2\*n\_r\_max) [integer,out]
- wpmat\_fac (2\*n\_r\_max,2) [real,out]

```
Called from updatewp()
Call to sqefa()
```

## 10.7.3 updateZ.f90

## **Quick access**

```
Variables workb, workc, worka, rhs1, maxthreads
Routines initialize_updatez(), get_zmat(), get_z10mat(), updatez()
```

- physical\_parameters (kbotv(), lffac(), ktopv()): Module containing the physical parameters
- init\_fields
- radial\_der (get\_ddr()): Radial derivatives functions

- constants (c\_dt\_z10\_ic(), c\_moi\_ic(), half(), two(), c\_moi\_ma(), c\_lorentz\_ic(), zero(), c\_z10\_omega\_ic(), four(), one(), c\_dt\_z10\_ma(), c\_moi\_oc(), y11\_norm(), c\_lorentz\_ma(), y10\_norm(), c\_z10\_omega\_ma()): module containing constants and parameters used in the code.
- blocking (lmstartb(), st\_map(), st\_sub\_map(), lo\_sub\_map(), nlmbs(), lmstopb(), lo\_map()): Module containing blocking information
- truncation(lm\_max(), n\_r\_max(), n\_cheb\_max(), l\_max()): This module defines the grid points and the truncation
- parallel\_mod: This module contains the blocking information
- rms\_helpers (hint2pol(), hint2tor()): This module contains several useful subroutines required to compute RMS diagnostics
- communications (get\_global\_sum())
- matrices (z10pivot(), lzmat(), zpivot(), zmat(), z10mat\_fac(), zmat\_fac(), z10mat(), lz10mat()): This module contains matricies for internal time step
- rms (diftor2hint(), dtvtor2hint(), diftoras2hint(), dtvtoras2hint()): This module contains the global array used when RMS force balance is requested
- precision\_mod: This module controls the precision used in MagIC
- horizontal\_data(dlh(), hdif\_v()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_to(), l\_rot\_ic(), l\_srma(), l\_correct\_amz(), l\_rot\_ma(), l\_correct\_ame(), l\_sric(), l\_z10mat(), l\_rmstest(), l\_update\_v()): Module containing the logicals that control the run
- radial\_functions (cheb\_norm(), d2cheb(), dcheb(), dbeta(), cheb(), rho0(), d\_costf\_init(), or2(), drx(), dlvisc(), ddrx(), or1(), r\_icb(), visc(), r(), i\_costf\_init(), beta(), r\_cmb())
- omp\_lib
- cosine\_transform(costf1())
- radial\_data(n\_r\_icb(), n\_r\_cmb())
- torsional\_oscillations (ddzasl()): This module contains information for TO calculation and output
- algebra (cgeslml(), cgesl(), sgefa())
- outrot(get angular moment())
- num\_param (amstart (), alpha ()): Module containing numerical and control parameters
- lmloop\_data(ulm(), llm())

- updatez\_mod/workc(:,:) [complex,private/allocatable]
- updatez\_mod/worka (:,:) [complex,private/allocatable]
- updatez\_mod/workb (:,:) [complex,private/allocatable]
- updatez mod/**rhs1** (::::) [complex,private/allocatable]

• updatez mod/maxthreads [integer, private]

## Subroutines and functions

```
subroutine \ {\tt updatez\_mod/initialize\_updatez} \ ()
```

```
Called from initialize Imloop()
```

**subroutine** updatez\_mod/**updatez** (z, dz, dzdt, dzdtlast, time, omega\_ma, d\_omega\_ma\_dtlast, omega\_ic, d\_omega\_ic\_dtlast, lorentz\_torque\_ma, lorentz\_torque\_malast, lorentz\_torque\_ic, lorentz\_torque\_iclast, w1, coex, dt, lrmsnext)

updates the toroidal potential z and its radial derivatives adds explicit part to time derivatives of z

## **Parameters**

- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*inout*]
- **dz** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*, *out*]
- **dzdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dzdtlast** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*inout*]
- **time** [real,in] :: Current time
- omega\_ma [real,out] :: Calculated OC rotation
- d\_omega\_ma\_dtlast [real,inout] :: Time derivative of OC rotation of previous step
- omega\_ic [real,out] :: Calculated IC rotation
- **d\_omega\_ic\_dtlast** [real,inout] :: Time derivative of IC rotation of previous step
- lorentz\_torque\_ma [real,in] :: Lorentz torque (for OC rotation)
- lorentz\_torque\_malast [real,in] :: Lorentz torque (for OC rotation) of previous step
- **lorentz torque ic** [real,in] :: Lorentz torque (for IC rotation)
- lorentz\_torque\_iclast [real,in] :: Lorentz torque (for IC rotation) of previous step
- w1 [real,in] :: Weight for time step
- coex [real,in] :: Factor depending on alpha
- **dt** [real,in] :: Time step interval
- **Irmsnext** [logical,in] :: Logical for storing update if (l\_RMS.and.l\_logNext)

```
Call to get_zmat(), get_z10mat(), cgesl(), cgeslml(), get_ddr(),
    get_angular_moment(), hint2tor()
```

```
subroutine updatez_mod/get_z10mat (dt, l, hdif, zmat, zpivot, zmat_fac)
```

Purpose of this subroutine is to construct and LU-decompose the inversion matrix z10mat for the implicit time step of the toroidal velocity potential z of degree l=1 and order m=0. This differs from the the normal zmat only if either the ICB or CMB have no-slip boundary condition and inner core or mantle are chosen to rotate freely (either kbotv=1 and/or ktopv=1).

## **Parameters**

- **dt** [real,in] :: Time step internal
- I [integer,in] :: Variable to loop over l's

- hdif [real,in] :: Value of hyperdiffusivity in zMat terms
- **zmat** (n\_r\_max,n\_r\_max) [real,out] :: LHS matrix to calculate z
- **zpivot** (*n\_r\_max*) [integer,out] :: Pivot to invert zMat
- **zmat\_fac** (*n\_r\_max*) [*real,out*] :: Inverse of max(zMat) for inversion

Called from updatez()

Call to sgefa()

**subroutine** updatez\_mod/**get\_zmat** (*dt*, *l*, *hdif*, *zmat*, *zpivot*, *zmat\_fac*)

Purpose of this subroutine is to contruct the time step matricies zmat(i,j) for the NS equation.

#### **Parameters**

- **dt** [real,in] :: Time interval
- 1 [integer,in] :: Variable to loop over degrees
- **hdif** [real,in] :: Hyperdiffusivity
- **zmat** (*n\_r\_max,n\_r\_max*) [*real,out*] :: Matrix with LHS of z equation
- **zpivot** (*n\_r\_max*) [integer,out] :: Pivot for zMat inversion
- **zmat\_fac** (*n\_r\_max*) [real,out] :: Inverse of max(zMat) for the inversion

Called from updatez()

Call to sgefa()

## 10.7.4 updateS.f90

## **Quick access**

```
Routines updates_ala(), updates(), get_smat(), initialize_updates(), get_s0mat()
```

- precision mod: This module controls the precision used in MagIC
- physical\_parameters (ktops(), kbots(), opr()): Module containing the physical parameters
- init\_fields(tops(), bots())
- horizontal\_data(dlh(), hdif\_s()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_anelastic\_liquid(), l\_update\_s()): Module containing the logicals that control the run
- radial\_functions (cheb\_norm(), drx(), kappa(), dlkappa(), dcheb(), cheb(), i\_costf\_init(), or2(), d2cheb(), orho1(), temp0(), beta(), or1(), d\_costf\_init(), dentropy0(), dtemp0(), ddrx(), otemp1())
- omp\_lib
- blocking (st\_map(), nlmbs(), lo\_map(), lmstartb(), lmstopb(), lo\_sub\_map()): Module containing blocking information

- cosine\_transform(costf1())
- radial\_data(n\_r\_icb(), n\_r\_cmb())
- truncation (lm\_max(), n\_r\_max(), n\_cheb\_max()): This module defines the grid points and the truncation
- algebra (cgeslml(), sgefa(), sgesl())
- parallel\_mod(chunksize(), rank()): This module contains the blocking information
- radial\_der (get\_drns(), get\_ddr()): Radial derivatives functions
- matrices (lsmat(), s0mat\_fac(), s0mat(), smat(), s0pivot(), smat\_fac(), spivot()): This module contains matrices for internal time step
- constants (one (), half (), zero (), two ()): module containing constants and parameters used in the code.
- num\_param (alpha ()): Module containing numerical and control parameters
- lmloop\_data(ulm(), llm())

- updates\_mod/**rhs1** (:,:,:) [complex,private/allocatable]
- updates\_mod/worka(:,:) [complex,private/allocatable]
- updates\_mod/workb (:,:) [complex,private/allocatable]
- updates\_mod/maxthreads [integer,private]

## **Subroutines and functions**

## **Parameters**

- **s** (ulm-(llm)+1,n\_r\_max) [complex,inout]
- **ds** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*, *out*]
- **dvsrlm** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*,*inout*]
- **dsdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*inout*]
- **dsdtlast** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*inout*]
- w1 [real,in] :: weight for time step!
- coex [real,in] :: factor depending on alpha
- **dt** [real,in] :: time step
- **nlmb** [integer,in]

Called from lmloop()

```
Call to get_drns(), get_s0mat(), get_smat(), sges1(), cges1ml(), get_ddr()
subroutine updates mod/updates ala(s, ds, w, dvsrlm, dsdt, dsdtlast, w1, coex, dt, nlmb)
          updates the entropy field s and its radial derivatives adds explicit part to time derivatives of s
          Parameters
                 • s (ulm-(llm)+1,n_r_max) [complex,inout]
                 • ds (ulm-(llm)+1,n_r_max) [complex,out]
                 • w (ulm-(llm)+1,n_r_max) [complex,in]
                 • dvsrlm (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dsdt (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dsdtlast (ulm-(llm)+1,n_r_max) [complex,inout]
                 • w1 [real,in] :: weight for time step!
                 • coex [real,in]:: factor depending on alpha
                 • dt [real,in] :: time step
                 • nlmb [integer,in]
          Called from lmloop()
          Call to get_drns(), get_s0mat(), get_smat(), sges1(), cges1ml(), get_ddr()
subroutine updates_mod/get_s0mat (dt, smat, spivot, smat_fac)
          Purpose of this subroutine is to contruct the time step matrix sMat0
          Parameters
                 • dt [real,in]
                 • smat (n_r_max,n_r_max) [real,out]
                 • spivot (n_r_max) [integer,out]
                 • smat_fac (n_r_max) [real,out]
          Called from updates_ala(), updates()
          Call to sgefa()
subroutine updates mod/get smat (dt, l, hdif, smat, spivot, smat fac)
          Purpose of this subroutine is to contruct the time step matricies sMat(i,j) and s0mat for the entropy
          equation.
          Parameters
                 • dt [real,in]
                 • 1 [integer,in]
```

• hdif [real,in]

• **spivot** (*n\_r\_max*) [integer,out]

• **smat** (*n\_r\_max*,*n\_r\_max*) [real,out]

```
• smat_fac (n_r_max) [real,out]

Called from updates_ala(), updates()

Call to sgefa()
```

## 10.7.5 updateB.f90

#### **Quick access**

```
Variables rhs2
Routines get_bmat(), updateb(), initialize_updateb()
```

- physical\_parameters (n\_r\_lcr(), o\_sr(), sigma\_ratio(), tmagcon(), imagcon(), opm(), ktopb(), kbotb(), conductance\_ma()): Module containing the physical parameters
- init\_fields(bpeaktop(), bpeakbot())
- radial\_der (get\_drns (), get\_ddr ()): Radial derivatives functions
- constants (three(), two(), pi(), one(), half(), zero()): module containing constants and parameters used in the code.
- blocking (lmstartb(), st\_map(), st\_sub\_map(), lo\_map(), nlmbs(), lmstopb(), lo\_sub\_map()): Module containing blocking information
- truncation (lm\_max(), n\_r\_max(), n\_cheb\_max(), n\_r\_ic\_maxmag(), n\_r\_totmag(), n\_r\_ic\_max(), n\_r\_totmag(), n\_r\_tot(), n\_cheb\_ic\_max()): This module defines the grid points and the truncation
- parallel\_mod (chunksize(), rank()): This module contains the blocking information
- rms\_helpers (hint2pol(), hint2tor()): This module contains several useful subroutines required to compute RMS diagnostics
- matrices (lbmat(), bmat(), jmat\_fac(), jmat(), jpivot(), bpivot(), bmat\_fac()): This module contains matrices for internal time step
- rms (dtbtoras2hint(), dtbpollmr(), dtbtor2hint(), dtbpolas2hint(), dtbpol2hint()): This module contains the global array used when RMS force balance is requested
- precision\_mod: This module controls the precision used in MagIC
- horizontal\_data(dlh(), dphi(), d\_l(), d\_lpl(), hdif\_b()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_rot\_ic(), l\_mag\_nl(), l\_cond\_ic(), l\_b\_nl\_cmb(), l\_lcr(), l\_b\_nl\_icb(), l\_update\_b()): Module containing the logicals that control the run
- omp\_lib
- radial\_functions (drx(), r\_cmb(), dcheb(), cheb(), d\_costf1\_ic\_init(), i\_costf1\_ic\_init(), d2cheb(), cheb\_ic(), o\_r\_ic(), d\_costf\_init(), d1lambda(), d2cheb\_ic(), d\_costf2\_ic\_init(), ddrx(), cheb\_norm(), dcheb\_ic(), r(), i\_costf\_init(), or2(), dr\_fac\_ic(), or1(), cheb\_norm\_ic(), i\_costf2\_ic\_init(), lambda())
- bext: Module containing the external field parameters

- cosine\_transform(costf1())
- radial\_data(n\_r\_icb(), n\_r\_cmb())
- algebra (cgeslml(), sgefa())
- num\_param(alpha()): Module containing numerical and control parameters
- lmloop\_data(llmmag(), ulmmag())
- radial\_der\_even(get\_ddr\_even())

- updateb\_mod/**rhs1** (:,:,:) [complex,private/allocatable]
- updateb mod/worka (:,:) [complex,private/allocatable]
- updateb\_mod/workb (:,:) [complex,private/allocatable]
- updateb\_mod/rhs2 (:,:,:) [complex,private/allocatable]
- updateb\_mod/maxthreads [integer,private]

## Subroutines and functions

```
subroutine updateb_mod/initialize_updateb()
```

```
Called from initialize_lmloop()
```

**subroutine** updateb\_mod/**updateb** (*b*, *db*, *ddb*, *aj*, *dj*, *ddj*, *dvxbhlm*, *dbdt*, *dbdtlast*, *djdt*, *djdtlast*, *b\_ic*, *db\_ic*, *ddb\_ic*, *aj\_ic*, *dj\_ic*, *ddj\_ic*, *dbdt\_iclast*, *djdt\_iclast*, *b\_nl\_cmb*, *aj\_nl\_cmb*, *aj\_nl\_icb*, *omega\_ic*, *wl*, *coex*, *dt*, *time*, *nlmb*, *lrmsnext*)

Calculated update of magnetic field potential and the time stepping arrays dbdtLast, ...

updates the magnetic field potentials b, aj and their derivatives, adds explicit part to time derivatives of b and j

#### **Parameters**

- **b** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,inout]
- **db** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,out]
- **ddb** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,out]
- **aj** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,inout]
- $\bullet \ \mathbf{dj} \ (ulmmag\text{-}(llmmag)\text{+}1, n\_r\_maxmag) \ [complex, out] \\$
- **ddj** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,out]
- **dvxbhlm** (*ulmmag*-(*llmmag*)+1,*n r maxmag*) [*complex*,*inout*]
- **dbdt** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*,*in*]
- **dbdtlast** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*,*inout*]
- **djdt** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*,*inout*]
- **djdtlast** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*, *inout*]
- **b\_ic** (*ulmmag-(llmmag*)+1,*n\_r\_ic\_maxmag*) [*complex,inout*]

```
• db_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
     • ddb_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
     • aj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,inout]
     • dj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
      • ddj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
     • dbdt_iclast (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,inout]
     • djdt_iclast (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,inout]
      • b_nl_cmb (*) [complex,in]
      • aj_nl_cmb (*) [complex,in]
     • aj_nl_icb (*) [complex,in]
     • omega_ic [real,in]
     • w1 [real,in] :: weight for time step!
     • coex [real,in]:: factor depending on alpha
     • dt [real,in]
      • time [real,in]
      • nlmb [integer,in]
     • lrmsnext [logical,in]
Called from lmloop()
Call to get_drns(), get_bmat(), cgeslml(), get_ddr(), get_ddr_even(),
    hint2pol(), hint2tor()
```

**subroutine** updateb\_mod/**get\_bmat** (dt, l, hdif, bmat, bpivot, bmat\_fac, jmat, jpivot, jmat\_fac)

Purpose of this subroutine is to contruct the time step matrices bmat(i,j) and ajmat for the dynamo equations.

## **Parameters**

```
• dt [real,in]
```

- I [integer,in]
- hdif [real,in]
- **bmat** (*n\_r\_totmag*,*n\_r\_totmag*) [real,out]
- **bpivot** (*n\_r\_totmag*) [integer,out]
- bmat\_fac (n\_r\_totmag) [real,out]
- **jmat** (*n\_r\_totmag*,*n\_r\_totmag*) [real,out]
- **jpivot** (*n\_r\_totmag*) [integer,out]
- jmat\_fac (n\_r\_totmag) [real,out]

Called from updateb()

Call to sgefa()

# 10.8 Non-linear part of the time stepping (radial loop)

## 10.8.1 radialLoop.f90

## **Quick access**

Routines finalize\_radialloop(), radialloop(), initialize\_radialloop()

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (kbotv(), ktopv()): Module containing the physical parameters
- logic (l\_mag\_kin(), lverbose(), l\_rot\_ic(), l\_mag\_nl(), l\_rot\_ma(), l\_dtb(), l\_mag(), l\_cond\_ic(), l\_cond\_ma(), l\_mag\_lf()): Module containing the logicals that control the run
- riterthetablocking\_mod(riterthetablocking\_t())
- blocking (sizethetab(), nthetabs()): Module containing blocking information
- fft\_jw: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- radial\_data (n\_r\_icb(), n\_r\_cmb(), nrstart(), nrstop(), nrstopmag(), nrstartmag())
- truncation(l\_maxmag(), lm\_max(), l\_max(), lmp\_max(), lm\_maxmag()): This module defines the grid points and the truncation
- graphout\_mod(graphout\_mpi\_header())
- parallel\_mod(n\_procs(), rank()): This module contains the blocking information
- riterthetablocking\_openmp\_mod(riterthetablocking\_openmp\_t())
- riteration\_mod(riteration\_t())
- constants (zero ()): module containing constants and parameters used in the code.
- riterthetablocking\_seq\_mod(riterthetablocking\_seq\_t())

#### Variables

## Subroutines and functions

```
subroutine radialloop/initialize_radialloop()
Called from magic
```

subroutine radialloop/finalize\_radialloop()

subroutine radialloop/radialloopg (l\_graph, l\_cour, l\_frame, time, dt, dtlast, ltocalc, ltonext, ltonext2, lhelcalc, lrmscalc, lviscbccalc, lfluxprofcalc, lperp-parcalc, dsdt, dwdt, dzdt, dpdt, dbdt, djdt, dvxbhlm, dvsrlm, lorentz\_torque\_ic, lorentz\_torque\_ma, br\_vt\_lm\_cmb, br\_vp\_lm\_cmb, br\_vt\_lm\_icb, br\_vp\_lm\_icb, hellmr, helalmr, helna2lmr, uhlmr, duhlmr, gradslmr, fconvlmr, fkinlmr, fvisclmr, fpoynlmr, freslmr, eperplmr, eparlmr, eperpaxilmr, eparaxilmr, dtrkc, dthkc)

This subroutine performs the actual time-stepping.

#### **Parameters**

- l\_graph [logical,in]
- **l\_cour** [logical,in]
- l\_frame [logical,in]
- time [real,in]
- dt [real,in]
- dtlast [real,in]
- **ltocalc** [logical,in]
- **ltonext** [logical,in]
- ltonext2 [logical,in]
- **lhelcalc** [logical,in]
- **Irmscalc** [logical,in]
- lviscbccalc [logical,in]
- Ifluxprofcalc [logical,in]
- **lperpparcalc** [logical,in]
- **dsdt** (*lm\_max,nrstop-(nrstart)+1*) [*complex,out*]
- **dwdt** (*lm\_max,nrstop-(nrstart*)+1) [*complex,out*]
- **dzdt** (*lm\_max,nrstop-*(*nrstart*)+1) [*complex,out*]
- **dpdt** (*lm\_max,nrstop-(nrstart)*+1) [*complex,out*]
- **dbdt** (*lm\_maxmag,nrstopmag-(nrstartmag)*+1) [*complex,out*]
- **djdt** (lm\_maxmag,nrstopmag-(nrstartmag)+1) [complex,out]
- **dvxbhlm** (*lm maxmag,nrstopmag-(nrstartmag)*+1) [complex,out]
- **dvsrlm** (*lm\_max,nrstop-(nrstart)*+1) [*complex,out*]
- lorentz\_torque\_ic [real,out]
- lorentz\_torque\_ma [real,out]
- **br\_vt\_lm\_cmb** (*lmp\_max*) [complex,out] :: product br\*vt at CMB
- br\_vp\_lm\_cmb (lmp\_max) [complex,out] :: product br\*vp at CMB
- **br\_vt\_lm\_icb** (*lmp\_max*) [complex,out] :: product br\*vt at ICB
- **br\_vp\_lm\_icb** (*lmp\_max*) [complex,out] :: product br\*vp at ICB

```
• hellmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • hel2lmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • helnalmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • helna2lmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • uhlmr (l max+1,nrstop-(nrstart)+1) [real,out]
      • duhlmr (l max+1,nrstop-(nrstart)+1) [real,out]
      • gradslmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • fconvlmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • fkinlmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • fvisclmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • fpoynlmr (l_maxmag+1,nrstopmag-(nrstartmag)+1) [real,out]
      • freslmr (l_maxmag+1,nrstopmag-(nrstartmag)+1) [real,out]
      • eperplmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • eparlmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • eperpaxilmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • eparaxilmr (l max+1,nrstop-(nrstart)+1) [real,out]
      • dtrkc (nrstop-(nrstart)+1) [real, out]
      • dthkc (nrstop-(nrstart)+1) [real, out]
Called from step_time()
Call to graphout_mpi_header()
```

## 10.8.2 rIteration.f90

## Quick access

**Routines** set\_steering\_variables()

## **Needed modules**

• precision\_mod: This module controls the precision used in MagIC

## **Types**

• type riteration\_mod/unknown\_type

## Type fields

- % nr [integer]
- % ltonext [logical]
- % dthkc [real]
- % dtrkc[real]

- % lmagnlbc [logical]
- % ltocalc [logical]
- % ltonext2 [logical]
- % 1\_frame [logical]
- % nbc [integer]
- % 1\_cour [logical]
- % lperpparcalc [logical]
- % lfluxprofcalc [logical]
- % lderiv [logical]
- % lviscbccalc [logical]
- % 1\_graph [logical]
- % lrmscalc[logical]
- % lhelcalc [logical]
- % isradialboundarypoint [logical]

## Subroutines and functions

## **Parameters**

- this [real]
- **l\_cour** [logical,in]
- **ltocalc** [logical,in]
- **ltonext** [logical,in]
- ltonext2 [logical,in]
- **Ideriv** [logical,in]
- **Irmscalc** [logical,in]
- **lhelcalc** [logical,in]
- l\_frame [logical,in]
- **lmagnlbc** [logical,in]
- l\_graph [logical,in]
- lviscbccalc [logical,in]
- Ifluxprofcalc [logical,in]
- **lperpparcalc** [logical,in]

## 10.8.3 rIterThetaBlocking.f90

#### **Quick access**

```
Routines transform_to_grid_space(), set_thetablocking(), deallocate_common_arrays(), transform_to_lm_space(), allocate_common_arrays()
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- leg\_helper\_mod(leg\_helper\_t())
- logic (l\_store\_frame(), l\_mag\_kin(), l\_cond\_ma(), l\_cond\_ic(), l\_b\_nl\_cmb(), l\_conv(), l\_rot\_ma(), l\_movie\_oc(), l\_to(), l\_anel(), l\_rot\_ic(), l\_mag\_nl(), l\_mag(), l\_dtb(), l\_ht(), l\_conv\_nl(), l\_mag\_lf(), l\_heat(), l\_b\_nl\_icb()): Module containing the logicals that control the run
- physical\_parameters (n\_r\_lcr(), ktops(), kbots()): Module containing the physical parameters
- radial\_functions(or2(), orho1())
- blocking (nfs ()): Module containing blocking information
- fft\_jw: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- legendre\_grid\_to\_spec
- radial\_data(nrstop(), n\_r\_icb(), n\_r\_cmb(), nrstart())
- truncation (lm\_max(), n\_r\_maxstr(), lmp\_max(), lm\_maxmag(), n\_theta\_maxstr(), n\_phi\_maxstr(), l\_max(), nrp(), lmp\_max\_dtb()): This module defines the grid points and the truncation
- legendre\_spec\_to\_grid(legtfg(), legtfgnomag())
- grid\_space\_arrays\_mod(grid\_space\_arrays\_t())
- nonlinear lm mod(nonlinear lm t())
- riteration\_mod(riteration\_t())
- nonlinear\_bcs(v\_rigid\_boundary())

## **Types**

• type riterthetablocking\_mod/unknown\_type

### Type fields

- % btvrlm(\*)[complex,allocatable]
- % btvzlm(\*) [complex,allocatable]
- % brvzlm(\*)[complex,allocatable]
- % bpvtsn2lm(\*)[complex,allocatable]
- % bpvtcotlm(\*)[complex,allocatable]

```
- % btvpcotlm(*)[complex,allocatable]
              - % brvplm (*) [complex, allocatable]
              - % bpvtlm(*)[complex,allocatable]
             - % btvzcotlm(*)[complex,allocatable]
             - % bpvrlm(*)[complex,allocatable]
              - % brvtlm (*) [complex,allocatable]
             - % btvpsn2lm(*)[complex,allocatable]
             - % btvplm (*) [complex, allocatable]
              - % btvzsn2lm(*)[complex,allocatable]
• type riterthetablocking_mod/unknown_type
          Type fields
              - % dzrstrlm(*)[real,allocatable]
             - % dzastrlm(*)[real,allocatable]
              - % dzlflm (*) [real,allocatable]
```

- % dzcorlm(\*)[real,allocatable]
- type riterthetablocking\_mod/unknown\_type

## Type fields

- % dtb\_arrays [dtb\_arrays\_t]
- % to\_arrays[to\_arrays\_t]
- % leg\_helper [leg\_helper\_t]
- % sizethetab [integer]
- % bslast (,,\*) [real,allocatable]
- % bzlast (,,\*) [real, allocatable]
- % bplast (,,\*) [real,allocatable]
- % nthetabs [integer]

### Subroutines and functions

```
subroutine riterthetablocking_mod/allocate_common_arrays (this)
```

### **Parameters this** [real]

subroutine riterthetablocking\_mod/deallocate\_common\_arrays(this)

## **Parameters this** [real]

subroutine riterthetablocking\_mod/set\_thetablocking (this, nthetabs, sizethetab)

- this [real]
- **nthetabs** [integer,in]
- **sizethetab** [integer,in]

#### **Parameters**

- this [real]
- **nthetastart** [integer,in]
- **nthetastop** [integer,in]
- **gsa** [grid\_space\_arrays\_t]

**Call to** legtfg(), legtfgnomag(), fft\_thetab(), v\_rigid\_boundary()

subroutine riterthetablocking\_mod/transform\_to\_lm\_space(this, nthetastart, nthetastart, nthetastart, gsa, nl\_lm)

#### **Parameters**

- this [real]
- **nthetastart** [integer,in]
- **nthetastop** [integer,in]
- **gsa** [grid\_space\_arrays\_t]
- **nl\_lm** [nonlinear\_lm\_t]

Call to fft\_thetab(), legtf3(), legtf2(), legtf1()

## 10.8.4 rIterThetaBlocking\_OpenMP.f90

#### **Quick access**

**Routines** finalize\_riterthetablocking\_openmp(), initialize\_riterthetablocking\_openmp(), do\_iteration\_thetablocking\_openmp()

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- leg\_helper\_mod(leg\_helper\_t())
- logic (l\_store\_frame(), l\_mag\_kin(), l\_cond\_ma(), l\_cond\_ic(), l\_b\_nl\_cmb(), l\_conv(), l\_rot\_ma(), l\_movie\_oc(), l\_anel(), l\_rot\_ic(), l\_mag\_nl(), l\_mag(), l\_dtb(), l\_ht(), l\_conv\_nl(), l\_mag\_lf(), l\_heat(), l\_b\_nl\_icb()): Module containing the logicals that control the run
- riterthetablocking\_mod(riterthetablocking\_t())
- radial\_functions(or2(), orho1())
- blocking (nfs ()): Module containing blocking information
- fft jw: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- radial\_data(n\_r\_icb(), n\_r\_cmb())
- torsional\_oscillations (gettofinish(), getto(), gettonext()): This module contains information for TO calculation and output

- truncation(lm\_max(), n\_r\_maxstr(), lmp\_max(), n\_theta\_maxstr(), n\_phi\_maxstr(), lmax(), nrp(), lmp max dtb()): This module defines the grid points and the truncation
- graphout\_mod(graphout\_mpi())
- dtb\_mod (get\_dh\_dtblm(), get\_dtblm()): This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output....
- nl\_special\_calc: This module allows to calculcate several diagnostics that need to be computed in the physical space (non-linear quantities)
- courant\_mod(courant())
- grid\_space\_arrays\_mod(grid\_space\_arrays\_t())
- nonlinear\_lm\_mod(nonlinear\_lm\_t())
- out\_movie(store\_movie\_frame())
- constants (zero ()): module containing constants and parameters used in the code.
- nonlinear\_bcs(get\_br\_v\_bcs())
- outrot(get\_lorentz\_torque())

## **Types**

• type riterthetablocking\_openmp\_mod/unknown\_type

#### Type fields

- % nthreads [integer]
- % lorentz\_torque\_ic (\*) [real,allocatable]
- % nl lm (\*) [nonlinear lm t,allocatable]
- % lorentz\_torque\_ma (\*) [real,allocatable]
- % gsa (\*) [grid\_space\_arrays\_t,allocatable]

### Subroutines and functions

function riterthetablocking\_openmp\_mod/getthistype (this)

**Parameters this** [real]

**Return getthistype** [character]

subroutine riterthetablocking\_openmp\_mod/initialize\_riterthetablocking\_openmp (this)

**Parameters this** [real]

subroutine riterthetablocking\_openmp\_mod/finalize\_riterthetablocking\_openmp (this)

**Parameters this** [real]

subroutine riterthetablocking\_openmp\_mod/do\_iteration\_thetablocking\_openmp (this,

nr, nbc, time, dt, dtlast, dsdt, dwdt, dzdt, dpdt, dbdt, djdt, dvxbhlm, dvsrlm,  $br_vt_lm_cmb$ ,  $br_vp_lm_cmb$ ,  $br\_vt\_lm\_icb,$ br\_vp\_lm\_icb, lorentz\_torque\_ic, lorentz\_torque\_ma, hellmr, hel2lmr, helnalmr, helna 2lmr,uhlmr, duhlmr, gradslmr, fconvlmr, fkinlmr, fvisclmr, fpoynlmr, freslmr, eperplmr, eparlmr, eperрахilmr, eparax-

#### **Parameters**

- this [real]
- **nr** [integer,in]
- **nbc** [integer,in]
- time [real,in]

ilmr)

- **dt** [real,in]
- dtlast [real,in]
- **dsdt** (\*) [complex,out]
- **dwdt** (\*) [complex,out]
- **dzdt** (\*) [complex,out]
- **dpdt** (\*) [complex,out]
- **dbdt** (\*) [complex,out]
- **djdt** (\*) [complex,out]
- dvxbhlm (\*) [complex,out]
- **dvsrlm** (\*) [complex,out]
- **br\_vt\_lm\_cmb** (\*) [complex,out]
- **br\_vp\_lm\_cmb** (\*) [complex,out]
- **br\_vt\_lm\_icb** (\*) [complex,out]
- **br\_vp\_lm\_icb** (\*) [complex,out]
- lorentz\_torque\_ic [real,out]
- lorentz\_torque\_ma [real,out]
- hellmr (\*) [real,out]
- **hel2lmr** (\*) [real,out]
- helnalmr (\*) [real,out]
- helna2lmr (\*) [real,out]
- **uhlmr** (\*) [real,out]
- duhlmr (\*) [real,out]
- gradslmr (\*) [real,out]
- fconvlmr (\*) [real,out]
- **fkinlmr** (\*) [real,out]
- **fvisclmr** (\*) [real,out]
- **fpoynlmr** (\*) [real,out]
- freslmr (\*) [real,out]
- **eperplmr** (\*) [real,out]
- eparlmr (\*) [real,out]
- eperpaxilmr (\*) [real,out]
- eparaxilmr (\*) [real,out]

```
Call to get_br_v_bcs(), get_lorentz_torque(), courant(), graphout_mpi(),
    get_helicity(), get_nlblayers(), get_fluxes(), get_perppar(),
    store_movie_frame(), get_dtblm(), gettonext(), getto(),
    gettofinish(), get_dh_dtblm()
```

## 10.8.5 get\_nl.f90

### **Types**

• type general\_arrays\_mod/unknown\_type

## 10.8.6 get\_td.f90

#### **Quick access**

Routines get\_td(), finalize(), set\_zero()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (n\_r\_lcr(), vischeatfac(), ohmlossfac(), corfac(), epsc(), ra()): Module containing the physical parameters
- horizontal\_data (hdif\_v(), dtheta3s(), dphi0(), dtheta2s(), dlh(), dphi(), dtheta4a(), dtheta1s(), dtheta3a(), hdif\_b(), dtheta1a(), dtheta2a(), dtheta4s()):

  Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_mag\_kin(), l\_rmstest(), l\_anel(), l\_corr(), l\_mag(), l\_conv(), l\_conv\_nl(), l\_anelastic\_liquid(), l\_mag\_lf(), l\_heat(), l\_mag\_nl()): Module containing the logicals that control the run
- radial\_functions (or4(), temp0(), rgrav(), or1(), r(), rho0(), or2(), beta(), epscprof())
- blocking (st\_map(), lmp2lmpa(), lm2lma(), lm2lms(), lm2l(), lmp2lmps(), lm2m(), lm2lmp()): Module containing blocking information
- fields (z\_rloc(), dw\_rloc(), w\_rloc()): This module contains the potential fields and their radial derivatives
- truncation(lm\_max(), l\_max(), lm\_maxmag()): This module defines the grid points and the truncation
- rms\_helpers (hint2pol(), hint2tor()): This module contains several useful subroutines required to compute RMS diagnostics
- constants (zero (), two ()): module containing constants and parameters used in the code.
- rms (advtor2hint (), lftor2hint (), lftoras2hint (), cortoras2hint (), lfpol2hint (), magas2hint (), preas2hint (), lfpollmr (), advpol2hint (), maglmr (), corpol2hint (), buo2hint (), lfpolas2hint (), buoas2hint (), geo2hint (), advpolas2hint (), arclmr (), arcas2hint (), mag2hint (), prelmr (), pre2hint (), buolmr (), geolmr (), corpolas2hint (), corpollmr (), advtoras2hint (), cortor2hint (), arc2hint (), advpollmr (), geoas2hint ()): This module contains the global array used when RMS force balance is requested
- leg\_helper\_mod(leg\_helper\_t())

#### **Types**

```
• type nonlinear_lm_mod/unknown_type
```

## Type fields

- % vxbplm(\*)[complex,allocatable]
- % vxbtlm (\*) [complex, allocatable]
- % advtlm (\*) [complex,allocatable]
- % vxbrlm(\*)[complex,allocatable]
- % lftlm (\*) [complex,allocatable]
- % vstlm(\*)[complex,allocatable]
- % vsplm(\*)[complex,allocatable]
- % ohmlosslm(\*)[complex,allocatable]
- % vsrlm(\*)[complex,allocatable]
- % lfrlm(\*)[complex,allocatable]
- % lfplm (\*) [complex,allocatable]
- % advplm(\*)[complex,allocatable]
- % advrlm(\*)[complex,allocatable]
- % vischeatlm(\*)[complex,allocatable]

#### **Subroutines and functions**

subroutine nonlinear\_lm\_mod/initialize (this, lmp\_max)

#### **Parameters**

- this [real]
- lmp\_max [integer,in]

subroutine nonlinear\_lm\_mod/finalize(this)

**Parameters this** [real]

subroutine nonlinear\_lm\_mod/set\_zero (this)

**Parameters this** [real]

subroutine nonlinear\_lm\_mod/output (this)

Parameters this [real]

Purpose of this to calculate time derivatives dwdt,dzdt,dpdt,dsdt,dbdt,djdt and auxiliary arrays dVS-rLM and dVxBhLM from non-linear terms in spectral form, contained in flmw1-3,flms1-3, flmb1-3 (input)

## **Parameters**

• this [real]

- **nr** [integer,in]
- **nbc** [integer,in] :: signifies boundary conditions
- **lrmscalc** [logical,in]
- **dvsrlm** (*lm\_max*) [complex,out]
- **dvxbhlm** (*lm\_maxmag*) [complex,out]
- **dwdt** (*lm max*) [complex,out]
- **dzdt** (*lm\_max*) [*complex,out*]
- **dpdt** (*lm\_max*) [complex,out]
- **dsdt** (*lm\_max*) [complex,out]
- **dbdt** (*lm\_maxmag*) [complex,out]
- **djdt** (*lm\_maxmag*) [*complex,out*]
- **leg\_helper** [leg\_helper\_t,in]

Call to hint2pol(), hint2tor()

## 10.8.7 nonlinear\_bcs.f90

### **Quick access**

**Routines** get\_br\_v\_bcs(), get\_b\_nl\_bcs(), v\_rigid\_boundary()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters(sigma\_ratio(), prmag(), conductance\_ma()): Module containing the physical parameters
- horizontal\_data (sn2(), costheta(), o\_sin\_theta(), dlh(), dphi(), dthetala(), dthetals()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- constants (two ()): module containing constants and parameters used in the code.
- radial\_functions(rho0(), r\_cmb(), r\_icb())
- blocking (lmp2lmpa(), nfs(), lm2l(), sizethetab(), lmp2lmps(), lm2m(), lm2lmp()): Module containing blocking information
- fft\_jw (fft\_thetab()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- legendre\_grid\_to\_spec(legtf2())
- radial\_data(n\_r\_icb(), n\_r\_cmb())
- truncation (n\_phi\_max(), lmp\_max(), nrp()): This module defines the grid points and the truncation

#### **Variables**

#### **Subroutines and functions**

```
subroutine nonlinear_bcs/get_br_v_bcs(br, vt, vp, omega, o\_r\_e\_2, o\_rho, n\_theta\_min, n\_theta\_block, br\_vt\_lm, br\_vp\_lm)
```

Purpose of this subroutine is to calculate the nonlinear term of the magnetic boundary condition for a conducting mantle or inner core in space (r,lm). Calculation is performed for the theta block:

```
n\_theta\_min <= n\_theta <= n\_theta\_min + n\_theta\_block - 1
```

On input br, vt and vp are given on all phi points and thetas in the specific block. On output the contribution of these grid points to all degree and orders is stored in br\_vt\_lm and br\_vp\_lm. Output is [r/sin(theta)\*Br\*U]=[(0,br\_vt\_lm,br\_vp\_lm)]

#### **Parameters**

- **br** (*nrp*,\*) [*real,in*] :: r\*\*2 \* B\_r
- vt (nrp,\*) [real,in] :: r\*sin(theta) U\_theta
- **vp** (*nrp*,\*) [*real*,*in*] :: r\*sin(theta) U\_phi
- omega [real,in] :: rotation rate of mantle or IC
- **o\_r\_e\_2** [real,in] :: 1/r\*\*2
- o\_rho [real,in] :: 1/rho0 (anelastic)
- n\_theta\_min [integer,in] :: start of theta block
- n\_theta\_block [integer,in] :: size of theta\_block
- **br\_vt\_lm** (*lmp\_max*) [complex,inout]
- **br\_vp\_lm** (*lmp\_max*) [complex,inout]

 $\textbf{Called from } \texttt{do\_iteration\_thetablocking\_seq()}, \textit{do\_iteration\_thetablocking\_openmp()}$ 

```
Call to fft_thetab(), legtf2()
```

## **Parameters**

- **bc** [character,in] :: Distinguishes 'CMB' and 'ICB'
- **br\_vt\_lm** (*lmp\_max*) [*complex,in*] :: [br\*vt/(r\*\*2\*sin(theta)\*\*2)]
- **br\_vp\_lm** (*lmp\_max*) [*complex,in*] :: [br\*vp/(r\*\*2\*sin(theta)\*\*2)
- **lm\_min\_b** [integer,in] :: limits of lm-block
- lm\_max\_b [integer,in] :: nonlinear bc for aj
- **b\_nl\_bc** (lm\_max\_b-lm\_min\_b+1) [complex,out]
- aj\_nl\_bc (lm\_max\_b-lm\_min\_b+1) [complex,out]

Called from step\_time()

**subroutine** nonlinear\_bcs/**v\_rigid\_boundary** (*nr*, *omega*, *lderiv*, *vrr*, *vtr*, *vpr*, *cvrr*, *dvrdtr*, *dvrdpr*, *dvtdpr*, *dvpdpr*, *nthetastart*)

Purpose of this subroutine is to set the velocities and their derivatives at a fixed boundary. While vt is zero, since we only allow for rotation about the z-axix, vp= r sin(theta) v\_phi =  $r^*2$  sin(theta)\*\*2 omega cvr=  $r^*2$  radial component of (curl v) =  $r^*2$  2 cos(theta) omega

#### **Parameters**

- **nr** [integer,in] :: no of radial grid point
- omega [real,in]
- **Ideriv** [logical,in] :: derivatives required?
- **vrr** (*nrp*,*nfs*) [real,out]
- **vtr** (*nrp*,*nfs*) [real,out]
- **vpr** (*nrp*,*nfs*) [real,out]
- **cvrr** (*nrp*,*nfs*) [real,out]
- **dvrdtr** (*nrp*,*nfs*) [real,out]
- **dvrdpr** (*nrp*,*nfs*) [real,out]
- **dvtdpr** (*nrp*,*nfs*) [real,out]
- **dvpdpr** (nrp,nfs) [real,out]
- **nthetastart** [integer,in] :: no of theta to start with

Called from transform\_to\_grid\_space()

## 10.9 Chebyshev polynomials and cosine transforms

## 10.9.1 chebyshev\_polynoms.f90

#### **Quick access**

## Needed modules

- precision\_mod: This module controls the precision used in MagIC
- constants (one (), four (), half (), two (), pi ()): module containing constants and parameters used in the code.
- logic (l\_newmap ()): Module containing the logicals that control the run

#### **Variables**

• chebyshev\_polynoms\_mod/get\_chebs [public]

#### **Subroutines and functions**

Construct Chebychev polynomials and their first, second, and third derivative up to degree n\_r at n\_r points x in the interval [a,b]. Since the Chebs are only defined in [-1,1] we have to use a map, mapping the points x points y in the interval [-1,1]. This map is executed by the subroutine cheb\_grid and has to be done before calling this program.

#### **Parameters**

- **n\_r** [integer,in] :: number of grid points
- a [real,in] :: interval boundaries [a,b]
- **b** [real,in]
- y (n\_r\_max) [real,in] :: n\_r grid points in interval [a,b]
- **n\_r\_max** [integer,in,] :: leading dimension of
- **cheb** (dim1,dim2) [real,out] :: cheb(i,j) is Chebychev pol.
- **dcheb** (dim1,dim2) [real,out] :: first derivative of cheb
- **d2cheb** (dim1,dim2) [real,out] :: second derivative o cheb
- **d3cheb** (dim1,dim2) [real,out] :: third derivative of cheb
- **dim1** [integer,in] :: dimensions of cheb,dcheb,....
- dim2 [integer,in]
- map\_fac1 (*n\_r\_max*) [real,in]
- map\_fac2 (*n\_r\_max*) [real,in]
- map\_fac3 (*n\_r\_max*) [real,in]

#### **Parameters**

- **n\_r** [integer,in] :: number of grid points
- a [real,in] :: interval boundaries [a,b]
- **b** [real,in]
- y (n\_r\_max) [real,in] :: n\_r grid points in interval [a,b]
- n\_r\_max [integer,in,] :: max number of radial points, dims of y
- **cheb** (dim1,dim2) [real,out] :: cheb(i,j) is Chebychev pol.
- **dcheb** (dim1,dim2) [real,out] :: first derivative of cheb
- **d2cheb** (dim1,dim2) [real,out] :: second derivative o cheb
- dim1 [integer,in] :: dimensions of cheb,dcheb,.....
- dim2 [integer,in]

Called from radial()

Construct Chebychev polynomials and their first, second, and third derivative up to degree n\_r at n\_r points x in the interval [a,b]. Since the Chebs are only defined in [-1,1] we have to use a map, mapping the points x points y in the interval [-1,1]. This map is executed by the subroutine cheb\_grid and has to be done before calling this program.

#### **Parameters**

- **n\_r** [integer,in] :: number of grid points
- a [real,in] :: interval boundaries [a,b]
- **b** [real,in]
- y (n\_r\_max) [real,in] :: n\_r grid points in interval [a,b]
- n\_r\_max [integer,in,] :: leading dimension of
- **cheb** (dim1,dim2) [real,out] :: cheb(i,j) is Chebychev pol.
- **dcheb** (dim1,dim2) [real,out] :: first derivative of cheb
- **d2cheb** (dim1,dim2) [real,out] :: second derivative o cheb
- d3cheb (dim1,dim2) [real,out] :: third derivative of cheb
- **dim1** [integer,in] :: dimensions of cheb,dcheb,....
- dim2 [integer,in]
- map fac1  $(n \ r \ max)$  [real,in]
- map\_fac2 (n\_r\_max) [real,in]
- map\_fac3 (*n\_r\_max*) [real,in]

**subroutine** chebyshev\_polynoms\_mod/**cheb\_grid** (a, b, n, x, y, a1, a2, x0, lbd)

Given the interval [a,b] the routine returns the n+1 points that should be used to support a Chebychev expansion. These are the n+1 extrema y(i) of the Chebychev polynomial of degree n in the interval [-1,1]. The respective points mapped into the interval of question [a,b] are the x(i).

**Note:** x(i) and y(i) are stored in the reversed order: x(1)=b, x(n+1)=a, y(1)=1, y(n+1)=-1

- a [real,in] :: interval boundaries
- **b** [real,in]
- n [integer,in] :: degree of Cheb polynomial to be represented by the grid points
- $\mathbf{x}$  (\*) [real,out] :: grid points in interval [a,b]
- y (\*) [real,out] :: grid points in interval [-1,1]
- **a1** [real,in]
- **a2** [real,in]
- **x0** [real,in]
- **lbd** [real,in]

```
Called from radial(), init_rnb(), chebintinit()
```

## 10.9.2 init\_costf.f90

#### **Quick access**

```
Routines init_costf1(), init_costf2()
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- useful (factorise()): library with several useful subroutines
- constants (sin60(), cos36(), half(), sin72(), pi(), sin36(), cos72(), one(), two()): module containing constants and parameters used in the code.

#### **Variables**

#### **Subroutines and functions**

```
subroutine init_costf/init_costf1 (n, i_costf_init, ni, d_costf_init, nd)
```

Purpose of this subroutine is to calculate and store several values that will be needed for a fast cosine transform of the first kind. The actual transform is performed by the subroutine costf1.

#### **Parameters**

- **n** [integer,in] :: No of grid points!
- i\_costf\_init (ni) [integer,out] :: array for integers
- **ni** [integer,in] :: dimension of i\_costf\_init
- **d\_costf\_init** (*nd*) [real,out] :: array for integers
- **nd** [integer,in] :: dimension of d costf init

```
Called from radial(), init_rnb(), chebintinit(), mapdatar()
```

Call to factorise()

```
subroutine init_costf/init_costf2 (n, i_costf_init, ni, d_costf_init, nd)
```

Purpose of this subroutine is to calculate several things needed for the cheb transform. Prepares costf2 for even number of grid points.

- **n** [integer,in] :: No of grid points!
- i\_costf\_init (ni) [integer,out] :: array for integers
- **ni** [integer,in] :: dimension of i\_costf\_init
- **d\_costf\_init** (*nd*) [real,out] :: array for integers
- **nd** [integer,in] :: dimension of i\_costf\_init

```
Called from radial()
Call to factorise()
```

## 10.9.3 cosine\_transform.f90

#### **Quick access**

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- constants (one (), half (), two ()): module containing constants and parameters used in the code.
- fft\_fac\_mod(fft\_fac\_real(), fft\_fac\_complex())
- truncation (lm\_max()): This module defines the grid points and the truncation

#### **Variables**

• cosine\_transform/costf1 [public]

#### Subroutines and functions

```
subroutine cosine_transform/costf1_complex (f, n_f_max, n_f_start, n_f_stop, f2, i_costf_init, d_costf_init)
```

Purpose of this subroutine is to perform a multiple cosine transforms for n+1 datapoints on the columns numbered n\_f\_start to n\_f\_stop in the array f(n\_f\_max,n+1) Depending whether the input f contains data or coeff arrays coeffs or data are returned in f.

## **Parameters**

- **f** (n\_f\_max,\*) [complex,inout] :: data/coeff input
- **n\_f\_max** [integer,in,] :: number of columns in f,f2
- **n\_f\_start** [integer,in] :: columns to be transformed
- **n\_f\_stop** [integer,in]
- **f2** (n\_f\_max,\*) [complex,out] :: work array of the same size as f
- i\_costf\_init (\*) [integer,in] :: prestored integers
- **d costf init** (\*) [real,in] :: prestored 1 numbers

Call to fft\_fac\_complex()

 $subroutine cosine\_transform/costf1\_complex\_1d(f,f2,i\_costf\_init,d\_costf\_init)$ 

```
• f (*) [complex,inout] :: data/coeff input
                  • f2 (*) [complex,out] :: work array of the same size as f
                 • i_costf_init (*) [integer,in] :: prestored integers
                 • d_costf_init (*) [real,in] :: prestored 1 numbers
           Call to fft fac complex()
subroutine cosine_transform/costf1_real(f, n_f_max, n_f_start, n_f_stop, f2, i_costf_init,
                                                     d_costf_init)
           Parameters
                  • f (n_f_max,*) [real,inout] :: data/coeff input
                  • n f max [integer, in, ] :: number of columns in f,f2
                 • n_f_start [integer,in] :: columns to be transformed
                 • n_f_stop [integer,in]
                  • f2 (n_f_max,*) [real,out] :: work array of the same size as f
                 • i_costf_init (*) [integer,in] :: prestored integers
                 • d_costf_init (*) [real,in] :: prestored 1 numbers
           Use truncation(lm_max_real())
           Call to fft_fac_real()
subroutine cosine transform/costf1 real 1d(f, f2, i costf init, d costf init)
           Parameters
                 • f (*) [real,inout] :: data/coeff input
                 • f2 (*) [real,out] :: work array of the same size as f
                 • i_costf_init (*) [integer,in] :: prestored integers
                  • d_costf_init (*) [real,in] :: prestored 1 numbers
           Call to fft_fac_real()
subroutine cosine_transform/costf2 (f, n_f_max, n_f_start, n_f_stop, f2, i_costf_init, d_costf_init,
                                              isign)
           Parameters
                  • f (n_f_max,*) [complex,inout] :: data/coeff input
                  • n_f_max [integer,in,] :: number of columns in y,y2
                  • n_f_start [integer,in] :: columns to be transformed
                 • n f stop [integer,in]
                 • f2 (n_f_max,*) [complex,out] :: work array of the same size as y
                  • i_costf_init (*) [integer,in] :: prestored integers
                  • d_costf_init (*) [real,in] :: prestored 1 numbers
                 • isign [integer, in] :: = +1 (-1) for forward (backward) transform
```

Called from get\_ddr\_even(), get\_ddrns\_even(), get\_drns\_even()

Call to fft\_fac\_complex()

## 10.9.4 fft fac.f90

### **Quick access**

```
Routines fft_fac_complex(), fft_fac_real()
```

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- constants (sin36(), sin60(), cos72(), sin72(), cos36()): module containing constants and parameters used in the code.

#### **Variables**

#### **Subroutines and functions**

```
subroutine fft_fac_mod/fft_fac_real (a, b, c, d, trigs, nv, l1, l2, n, ifac, la) main part of Fourier / Chebychev transform called in costf1, costf2
```

#### **Parameters**

- **a** (\*) [real,in]
- **b** (\*) [real,in]
- **c** (\*) [real,out]
- **d** (\*) [real,out]
- **trigs** (2 \* n) [real,in]
- **nv** [integer,in]
- **l1** [integer,in]
- 12 [integer,in]
- **n** [integer,in,]
- ifac [integer,in]
- la [integer,in]

Called from costfl\_real(), costfl\_real\_1d()

```
subroutine fft_fac_mod/fft_fac_complex (a, b, c, d, trigs, nv, l1, l2, n, ifac, la) main part of Fourier / Chebychev transform called in costf1, costf2
```

- **a** (\*) [complex,in]
- **b** (\*) [complex,in]
- **c** (\*) [complex,out]
- **d** (\*) [complex,out]

```
• trigs (2 * n) [real,in]
```

- **nv** [integer,in]
- **l1** [integer,in]
- **12** [integer,in]
- **n** [integer,in,]
- ifac [integer,in]
- la [integer,in]

Called from costf2(), costf1\_complex\_1d(), costf1\_complex()

# 10.10 Legendre transforms

## 10.10.1 plms.f90

#### **Quick access**

```
Routines plm_thetaas(), plm_theta()
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- constants (one (), osq4pi (), two ()): module containing constants and parameters used in the code.

## **Variables**

## **Subroutines and functions**

#### **Parameters**

- theta [real,in] :: angle in degrees
- max\_degree [integer,in] :: required max degree of plm
- max\_order [integer,in] :: required max order of plm
- m0 [integer,in] :: basic wave number
- plma (ndim\_plma) [real,out] :: ass. legendres at theta
- **dtheta\_plma** (ndim\_plma) [real,out] :: their theta derivative
- ndim\_plma [integer,in] :: dimension of plma and dtheta\_plma
- **norm** [integer,in] :: =0 fully normalised

```
Called from outto(), getegeos(), lnpas2tr(), horizontal(), outpv()
```

**subroutine** plms\_theta/**plm\_thetaas** (theta, max\_degree, plma, dtheta\_plma, ndim\_plma, norm)

The produces the plm for all degrees and order=0 for a given theta plus dtheta\_plma=sin(theta)\* (d plm)/(d theta)

**Norm determins the normalisation:** n=0 – surface normalised, n=1 – Schmidt normalised, n=2 – fully normalised.

#### **Parameters**

- theta [real,in] :: angle in degrees
- max\_degree [integer,in] :: required max degree of plm
- plma (ndim\_plma) [real,out] :: ass. legendres at theta
- **dtheta\_plma** (ndim\_plma) [real,out] :: their theta derivative
- ndim\_plma [integer,in] :: dimension of plma and dtheta\_plma
- **norm** [integer,in] :: =0 fully normalised

Called from horizontal ()

## 10.10.2 legendre\_helpers.f90

#### **Quick access**

Routines legprep(), legprep\_ic(), initialize(), legprepg()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- grenoble (b0(), ddb0(), db0(), lgrenoble()): This module contains all variables for the case of an imposed IC dipole
- horizontal\_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_mag\_kin(), l\_mag(), l\_conv(), l\_movie\_oc(), l\_mag\_lf(), l\_heat(), l\_fluxprofs()): Module containing the logicals that control the run
- radial\_functions(or2())
- blocking (1m2m(), 1m2(), 1m21()): Module containing blocking information
- constants (one (), zero (), two ()): module containing constants and parameters used in the code.
- fields (omega\_ic(), p\_rloc(), dj\_rloc(), dz\_rloc(), dw\_rloc(), db\_rloc(), ddw\_rloc(), b\_rloc(), omega\_ma(), ds\_rloc(), ddb\_rloc(), z\_rloc(), aj\_rloc(), s\_rloc(), dp\_rloc(), w\_rloc()): This module contains the potential fields and their radial derivatives
- radial\_data(n\_r\_icb(), n\_r\_cmb())
- torsional\_oscillations (ddzasl()): This module contains information for TO calculation and output
- truncation (lm\_max(), l\_max()): This module defines the grid points and the truncation

#### **Types**

```
• type leg_helper_mod/unknown_type
```

## Type fields

- % dlhdw (\*) [complex, allocatable]
- % ddzas (\*) [real,allocatable]
- % **vhc** (\*) [complex,allocatable]
- % omegama [real]
- % bcmb (\*) [complex,allocatable]
- % dvhdrc (\*) [complex,allocatable]
- % dlhw (\*) [complex,allocatable]
- % dlhz (\*) [complex,allocatable]
- % **sr** (\*) [complex,allocatable]
- % cbhc (\*) [complex,allocatable]
- % prer (\*) [complex,allocatable]
- % cbhg (\*) [complex,allocatable]
- % dlhb (\*) [complex,allocatable]
- % dsr(\*) [complex,allocatable]
- % zas (\*) [real,allocatable]
- % bhg (\*) [complex,allocatable]
- % dzas (\*) [real, allocatable]
- % vhg (\*) [complex,allocatable]
- % dlhj(\*)[complex,allocatable]
- % bhc (\*) [complex,allocatable]
- % dpr (\*) [complex,allocatable]
- % omegaic [real]
- % dvhdrg (\*) [complex,allocatable]

#### **Variables**

### **Subroutines and functions**

subroutine leg\_helper\_mod/initialize(this, lm\_max, lm\_maxmag, l\_max)

- this [real]
- lm\_max [integer,in]
- lm\_maxmag [integer,in]
- l\_max [integer,in]

Purpose of this subroutine is to prepare Legendre transforms from (r,l,m) space to (r,theta,m) space by calculating auxiliary arrays dpdw,dpddw, ...... dLhj which contain combinations of harmonic coeffs multiplied with (l,m)-dependend factors as well as the radial dependence:

- •nBc =0 standard inner radial grid point
- •nBc =1 radial velocity zero, spatial derivs not needed
- •nBc =2 all velocity comp. zero, spatial derivs not needed

lDeriv=.true. field derivatives required

#### **Parameters**

- this [real]
- **nr** [integer,in] :: radial level
- **nbc** [integer,in] :: boundary condition
- Ideriv [logical,in] :: get also field derivatives !
- **Irmscalc** [logical,in] :: Rms force balance ?
- **l\_frame** [logical,in] :: Calculate movie frame?
- **Itonext** [logical,in] :: for TO output
- **Itonext2** [logical,in]
- **ltocalc** [logical,in]

**subroutine** leg\_helper\_mod/**legprep** (w, dw, ddw, z, dz, dlh, lm\_max, l\_max, minc, r, lderiv, lhor, dlhw, vhg, vhc, dlhz, cvhg, cvhc)

Purpose of this subroutine is to prepare Legendre transforms from (r,l,m) space to (r,theta,m) space by calculating auxiliary arrays w, dw, ddw, ...... which contain combinations of harmonic coeffs multiplied with (l,m)-dependend factors as well as possible the radial dependencies.

1Deriv=.true. field derivatives required for curl of field

- w (lm\_max) [complex,in]
- **dw** (*lm\_max*) [*complex*, *in*]
- **ddw** (*lm max*) [complex,in]
- **z** (lm\_max) [complex,in]
- **dz** (*lm\_max*) [*complex,in*]
- dlh (lm\_max) [real,in]
- lm\_max [integer,in,]
- l\_max [integer,in]
- minc [integer,in]
- **r** [real,in]
- **Ideriv** [logical,in]

- **lhor** [logical,in]
- dlhw (\*) [complex,out]
- **vhg** (\*) [complex,out]
- **vhc** (\*) [complex,out]
- **dlhz** (\*) [complex,out]
- cvhg (\*) [complex,out]
- cvhc (\*) [complex,out]

Called from fields\_average()

**subroutine** leg\_helper\_mod/**legprep\_ic** (w, dw, ddw, z, dz, dlh, lm\_max, l\_max, minc, r, r\_icb, lderiv, lhor, lcondic, dlhw, vhg, vhc, dlhz, cvhg, cvhc)

Purpose of this subroutine is to prepare Legendre transforms from (r,l,m) space to (r,theta,m) space by calculating auxiliary arrays dLhw,vhG, ........ which contain combinations of harmonic coeffs multiplied with (l,m)-dependend factors as well as possible the radial dependencies.

1Deriv=.true. field derivatives required for curl of field

Note: This routine is used for the inner core magnetic field which has a special radial function ansatz. It can also be used to prepare the calculation of a field in an insulating inner core for lCondIC=.false.. For this the w has to be the outer core poloidal field and nR is the grid point for the ICB. In any case legTF can be used for the following Legendre transform and fftJW for the Fourier transform.

- w (lm max) [complex,in]
- **dw** (*lm\_max*) [complex,in]
- **ddw** (*lm\_max*) [complex,in]
- **z** (lm\_max) [complex,in]
- **dz** (*lm\_max*) [*complex,in*]
- **dlh** (*lm\_max*) [*real,in*]
- lm\_max [integer,in,]
- **l\_max** [integer,in]
- minc [integer,in]
- **r** [real,in]
- r\_icb [real,in]
- **Ideriv** [logical,in]
- **lhor** [logical,in]
- **lcondic** [logical,in]
- **dlhw** (*lm\_max*) [*complex,out*]
- **vhg** (*lm\_max*) [*complex,out*]
- **vhc** (*lm\_max*) [*complex,out*]
- dlhz (lm\_max) [complex,out]
- cvhg (lm max) [complex,out]

• cvhc (lm\_max) [complex,out]

Called from graphout\_ic(), store\_movie\_frame\_ic()

## 10.10.3 legendre\_spec\_to\_grid.f90

#### **Quick access**

Routines legtfgnomag(), lmas2pt(), legtf(), legtfg()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- leg\_helper\_mod(leg\_helper\_t())
- horizontal\_data(plm(), dplm(), d\_mc2m(), lstop(), lstart(), lmodd(), osn2()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_ht (), l\_heat ()): Module containing the logicals that control the run
- blocking (lm2mc(), sizethetab(), nfs(), lm2()): Module containing blocking information
- constants (one (), half (), zero ()): module containing constants and parameters used in the code.
- truncation (lm\_max(), l\_max(), n\_m\_max(), nrp()): This module defines the grid points and the truncation
- parallel\_mod (rank ()): This module contains the blocking information

#### **Variables**

#### Subroutines and functions

Legendre transform from (nR,l,m) to (nR,nTheta,m) [spectral to grid] where nTheta numbers the colatitudes and l is the degree of the spherical harmonic representation.

Transforms entropy, velocity and magnetic field components and terms involving spatial derivatives. The symmetry properties of the P\_lm with respect to the equator are used. The equatorially antisymmetric (EA) contribution is added to (subracted from ) the equatorially symmetric (ES) contribution in northern (southern) hemisphere.

•nBc: (input) accounts for special conditions on radial boundaries

- -nBc=2 [we are dealing with a no slip boundary, v\_r and v\_theta are] zero and v\_phi=r sin(theta) omega, where omega is the rotation rate of the boundary (mantle of IC), only magn. field terms are calculated, v is set later.
- -nBc=1 [a free slip bounday: v\_r is zero, derivatives of v and B] are not needed, only components of v,B and entropy are calculated
- -nBc=0: normal case, interior grid point

- •lDeriv=.true. : (input) calculate derivatives
- •nThetaStart : (input) transformation is done for the range of points nThetaStart <= nTheta <= nThetaStart-1+sizeThetaB
- •Plm: associated Legendre polynomials
- •dPlm: sin(theta) d Plm / d theta
- •osn2: 1/sin(theta)^2
- •vrc, ...., drSc: (output) components in (nTheta,m)-space
- •dLhw,...,cbhC: (input) help arrays calculated in s\_legPrep.f

- **nbc** [integer,in]
- Ideriv [logical,in]
- lviscbccalc [logical,in]
- Ifluxprofcalc [logical,in]
- nthetastart [integer,in]
- **vrc** (*nrp*,*nfs*) [real,out]
- **vtc** (*nrp*,*nfs*) [real,out]
- **vpc** (*nrp*,*nfs*) [real,out]
- **dvrdrc** (*nrp*,*nfs*) [real,out]
- **dvtdrc** (nrp,nfs) [real,out]
- **dvpdrc** (nrp,nfs) [real,out]
- **cvrc** (*nrp*,*nfs*) [real,out]
- **dvrdtc** (*nrp*,*nfs*) [real,out]
- **dvrdpc** (*nrp*,*nfs*) [real,out]
- **dvtdpc** (*nrp*,*nfs*) [real,out]
- **dvpdpc** (*nrp*,*nfs*) [real,out]
- **brc** (*nrp*,*nfs*) [real,out]
- **btc** (*nrp*,*nfs*) [real,out]
- **bpc** (*nrp*,*nfs*) [real,out]
- **cbrc** (*nrp*,*nfs*) [real,out]
- **cbtc** (*nrp*,*nfs*) [real,out]
- **cbpc** (*nrp*,*nfs*) [real,out]
- **sc** (*nrp*,*nfs*) [*real*,*out*]
- **drsc** (nrp,nfs) [real,out]
- **dsdtc** (nrp,nfs) [real,out]
- **dsdpc** (*nrp*,*nfs*) [real,out]
- **pc** (*nrp*,*nfs*) [real,out]

• leg\_helper [leg\_helper\_t]

Called from transform\_to\_grid\_space()

Same as legTFG for non-magnetic cases

#### **Parameters**

- **nbc** [integer,in]
- Ideriv [logical,in]
- lviscbccalc [logical,in]
- **Ifluxprofcalc** [logical,in]
- nthetastart [integer,in]
- **vrc** (*nrp*,*nfs*) [real,out]
- **vtc** (*nrp*,*nfs*) [real,out]
- **vpc** (*nrp*,*nfs*) [real,out]
- **dvrdrc** (nrp,nfs) [real,out]
- **dvtdrc** (nrp,nfs) [real,out]
- **dvpdrc** (nrp,nfs) [real,out]
- **cvrc** (nrp,nfs) [real,out]
- **dvrdtc** (nrp,nfs) [real,out]
- **dvrdpc** (nrp,nfs) [real,out]
- **dvtdpc** (*nrp*,*nfs*) [real,out]
- **dvpdpc** (*nrp*,*nfs*) [real,out]
- sc (nrp,nfs) [real,out]
- **drsc** (*nrp*,*nfs*) [real,out]
- **dsdtc** (nrp,nfs) [real,out]
- **dsdpc** (nrp,nfs) [real,out]
- **pc** (*nrp*,*nfs*) [real,out]
- leg\_helper [leg\_helper\_t]

Called from transform\_to\_grid\_space()

subroutine legendre\_spec\_to\_grid/legtf (dlhw, vhg, vhc, dlhz, cvhg, cvhc, l\_max, minc, nthetastart, sizethetab, plm, dplm, lhor, lderiv, vrc, vtc, vpc, cvrc,
cvtc, cvpc)

'Legendre transform' from (nR,l,m) to (nR,nTheta,m) [spectral to grid] where nTheta numbers the colatitudes and l and m are degree and order of the spherical harmonic representation.

Calculates all three spherical components vrc,vtc,vpc of a field as well as its curl (cvrc,cvtc,cvpc) that is given a spherical harmonis poloidal toroidal decomposition. s\_legPrep.f has to be called first

and provides the input fields dLhW, ..... The symmetry properties of the P\_lm with respect to the equator are used. The equatorially anti-symmetric (EA) contribution is added to (subracted from ) the equatorially symmetric (ES) contribution in northern (southern) hemisphere.

Output is given for all sizeThetaB colatitudes in a colatitude block that starts with colatitude nThetaStart. At output, each component in the northern hemisphere is followed by the component in the southern hemisphere. The Plms and dPlms=sin(theta) d Plm / d theta are only given for the colatitudes in the northern hemisphere.

```
•dLhw,...,cvhC: (input) arrays provided by s_legPrep.f
```

•l\_max: (input) maximum spherical harmonic degree

•minc: (input) azimuthal symmetry

•nThetaStart : (input) transformation is done for the range of points nThetaStart <= nTheta <= nThetaStart-1+sizeThetaB

•sizeThetaB: (input) size theta block

•Plm: (input) associated Legendre polynomials

•dPlm: (input) sin(theta) d Plm / d theta

•lHor=.true. : (input) calculate horizontal componenst

•lDeriv=.true. : (input) calculate curl of field

•vrc, ...,cvpc : (output) components in (nTheta,m)-space

- dlhw (\*) [complex,in]
- **vhg** (\*) [complex,in]
- **vhc** (\*) [complex,in]
- **dlhz** (\*) [complex,in]
- cvhg (\*) [complex,in]
- cvhc (\*) [complex,in]
- l\_max [integer,in]
- minc [integer,in]
- nthetastart [integer,in]
- sizethetab [integer,in]
- **plm** (*lm\_max*,\*) [*real*,*in*]
- **dplm** (*lm\_max*,\*) [*real,in*]
- **lhor** [logical,in]
- Ideriv [logical,in]
- **vrc** (*nrp*,\*) [real,out]
- **vtc** (*nrp*,\*) [*real*,*out*]
- **vpc** (*nrp*,\*) [real,out]
- cvrc (nrp,\*) [real,out]
- cvtc (nrp,\*) [real,out]

• **cvpc** (*nrp*,\*) [real,out]

Called from graphout\_ic(), fields\_average(), store\_movie\_frame\_ic()

**subroutine** legendre\_spec\_to\_grid/**lmas2pt** (alm, aij, nthetastart, nthetablocksize)

Spherical harmonic transform from alm(1) to aij(theta) Done within the range [nThetaStart,n\_thetaStart+nThetaBlockSize-1] only considering axisymmetric contributions. alm contains only m=0 coefficients

#### **Parameters**

- **alm** (\*) [real,in] :: field in (l,m)-space
- aij (\*) [real,out] :: field in (theta,phi)-space
- **nthetastart** [integer,in] :: first theta to be treated
- nthetablocksize [integer,in]

Called from outperppar(), outmisc(), outpar()

## 10.10.4 legendre\_grid\_to\_spec.f90

#### **Quick access**

Routines legtfas(), legtfas2(), legtf3(), legtf2(), legtf1()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- horizontal\_data (lstartp(), wplm(), lstopp(), lmoddp()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- truncation(lmp\_max(), n\_m\_max(), nrp(), n\_theta\_max()): This module defines the grid points and the truncation
- blocking (sizethetab(), nfs()): Module containing blocking information

#### **Variables**

#### Subroutines and functions

```
subroutine legendre_grid_to_spec/legtf1 (nthetastart, fllm, fltm)
```

Legendre transform (n\_r,n\_theta,m) to (n\_r,l,m) [grid to spectral] for 2 arrays f1TM (input) to f1LM (output) One call to this routine does part of the transform by summation over theta points in one theta block: nThetaStart,..,nThetaStart+n\_theta\_block-1

- **nthetastart** [integer,in] :: First no of theta on block
- **f1lm** (*lmp\_max*) [*complex,inout*]
- **f1tm** (*nrp*,*nfs*) [real,in]

```
Called from inits(), transform to lm space(), initv()
```

```
subroutine legendre_grid_to_spec/legtf2 (nthetastart, fllm, f2lm, f1tm, f2tm)
```

Legendre transform (n\_r,n\_theta,m) to (n\_r,l,m) [grid to spectral] for 2 arrays f1TM,f2TM (input) to f1LM,f2LM (output) One call to this routine does part of the transform by summation over theta points in on theta block: nThetaStart,...,nThetaStart+n\_theta\_block-1

#### **Parameters**

- **nthetastart** [integer,in] :: First no of theta on block
- **f1lm** (*lmp\_max*) [*complex*, *inout*]
- **f2lm** (*lmp\_max*) [complex,inout]
- **f1tm** (*nrp*,*nfs*) [real,in]
- **f2tm** (*nrp*,*nfs*) [*real*,*in*]

Called from get\_dtblm(), get\_br\_v\_bcs(), transform\_to\_lm\_space()

```
subroutine legendre_grid_to_spec/legtf3 (nthetastart, fllm, f2lm, f3lm, f1tm, f2tm, f3tm)
```

Legendre transform (n\_r,n\_theta,m) to (n\_r,l,m) [grid to spectral] for 2 arrays ancl1/2/3 (input) to flm1/2/3 (output) One call to this routine does part of the transform by summation over theta points in on theta block: nThetaStart,...,nThetaStart+n\_theta\_block-1

#### **Parameters**

- **nthetastart** [integer,in] :: First no of theta on block
- **f1lm** (*lmp\_max*) [*complex,inout*]
- **f2lm** (*lmp max*) [complex,inout]
- **f3lm** (*lmp\_max*) [complex,inout]
- **f1tm** (*nrp*,*nfs*) [real,in]
- **f2tm** (*nrp*,*nfs*) [*real*,*in*]
- **f3tm** (*nrp*,*nfs*) [*real*,*in*]

Called from get dtblm(), transform to lm space()

```
subroutine legendre_grid_to_spec/legtfas (flm1, ft1, lmmax, nthetastart, sizethetab)
```

Legendre transform (n\_r,n\_theta,m) to (n\_r,l,m) [grid to spectral] for 2 arrays ancl1/2 (input) to flm1/2 (output) One call to this routine does part of the transform by summation over theta points in on theta block: n theta min,...,n theta min+n theta block-1

#### **Parameters**

- **flm1** (\*) [real,out]
- ft1 (\*) [real,in]
- Immax [integer,in] :: Number of modes to be processed
- **nthetastart** [integer,in] :: First no of theta on block
- sizethetab [integer,in] :: Size of theta block

Called from outto(), get nlblayers(), get fluxes()

subroutine legendre\_grid\_to\_spec/legtfas2 (flm1, flm2, ft1, ft2, lmmax, nthetastart, sizethetab)

Legendre transform (n\_r,n\_theta,m) to (n\_r,l,m) [grid to spectral] for 2 arrays ancl1/2 (input) to flm1/2 (output) One call to this routine does part of the transform by summation over theta points in on theta block: n\_theta\_min,..,n\_theta\_min+n\_theta\_block-1

#### **Parameters**

- flm1 (\*) [real,out]
- flm2 (\*) [real,out]
- **ft1** (\*) [real,in]
- ft2 (\*) [real,in]
- Immax [integer,in] :: Number of modes to be processed
- **nthetastart** [integer,in] :: First no of theta on block
- **sizethetab** [integer,in] :: Size of theta block

```
Called from get_helicity(), outto(), get_perppar(), get_nlblayers(),
    get_fluxes(), getto()
```

## 10.11 Fourier transforms

## 10.11.1 fftJW.f90

#### **Description**

This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5

### **Quick access**

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- constants (sin60(), cos36(), half(), sin72(), pi(), sin36(), cos72(), one(), two()): module containing constants and parameters used in the code.
- blocking: Module containing blocking information
- useful (factorise()): library with several useful subroutines
- truncation: This module defines the grid points and the truncation
- parallel\_mod: This module contains the blocking information

#### **Variables**

- fft\_jw/i\_fft\_init (100) [integer,private]
- fft\_jw/nd[integer,private]
- fft\_jw/**d\_fft\_init** (:) [real,private/allocatable]
- fft\_jw/ni [integer,private/parameter=100]

### **Subroutines and functions**

```
subroutine fft_jw/init_fft (n)
```

Purpose of this subroutine is to calculate and store several values that will be needed for a fast fft transform. The actual transform is performed by the subroutine fftJW.

```
Parameters n [integer,in]:: Dimension of problem, number of grid points

Called from horizontal()
```

```
Call to factorise()
```

```
subroutine fft_jw/fft_to_real (f, ld_f, nrep)
```

#### **Parameters**

- **f** (ld\_f,nrep) [real,inout]
- ld\_f [integer,in,]
- nrep [integer,in,]

```
Called from getpvptr(), getdvptr()
```

```
Call to fft jw()
```

```
subroutine fft_jw/fft_thetab(f, dir)
```

#### **Parameters**

- **f** (*nrp*,*nfs*) [real,inout]
- dir [integer,in] :: back or forth transform

```
Called from transform_to_grid_space(), graphout_ic(), inits(),
    get_b_surface(), get_dtblm(), fields_average(), get_br_v_bcs(),
    lm2pt(), transform_to_lm_space(), get_bpol(), initv(), get_btor(),
    store_movie_frame_ic()
```

Call to fftjw()

```
subroutine fft_jw(a, ld_a, n, isign, nsize, wrk, wd1, wd2, i_fft_init, d_fft_init)
```

The routines has been adopted by Gary Glatzmaier and has subsequently been modified by Uli Christensen and Johannes Wicht

It performs a number of simultaneous real/half-complex periodic fast fourier transforms or corresponding inverse transforms, using ordinary spatial order of gridpoint values. given a set of real data vectors, the package returns a set of "half-complex" fourier coefficient vectors, or vice versa. the length of the transforms must be an even number that has no other factors except possibly powers of 2, 3, and 5. this version of fft991 is optimized for use on the cray-1.

```
on input a(ld_a,*)
```

an array of length (ld\_a,nsize) containing the input data or coefficient vectors. This array is overwritten by the results.

n the length of each transform (see definition of transforms, below).

**nsize** the number of transforms to be done simultaneously.

#### isign

- = +1 for a transform from fourier coefficients to gridpoint values.
- = -1 for a transform from gridpoint values to fourier coefficients.

on output a if isign = +1, and n\_theta\_max coefficient vectors are supplied each containing the sequence

```
a(0),b(0),a(1),b(1),...,a(n/2),b(n/2) (n+2 values)
```

then the result consists of n\_theta\_max data vectors each containing the corresponding n+2 gridpoint values

```
for fft991, x(0), x(1), x(2),...,x(n-1),0,0. (n+2) real values with x(n)=x(n+1)=0
```

```
when isign = +1, the transform is defined by x(j)=sum(k=0,...,n-1)(c(k)*exp(2*i*j*k*pi/n)) where c(k)=a(k)+i*b(k) and c(n-k)=a(k)-i*b(k) and i=sqrt (-1) for k=0,...,n/2 i.e., (n/2+1) complex values with c(0)=c(n)=a(0) and c(n/2)=a(n/2)=0
```

if isign = -1, and n\_theta\_max data vectors are supplied each containing a sequence of gridpoint values x(j) as defined above, then the result consists of n\_theta\_max vectors each containing the corresponding fourier cofficients a(k), b(k),  $0 \le k$ . le n/2.

```
when isign = -1, the inverse transform is defined by c(k)=(1/n)*sum(j=0,...,n-1)(x(j)*exp(-2*i*j*k*pi/n)) where c(k)=a(k)+i*b(k) and i=sqrt(-1) for k=0,...,n/2
```

a call with isign=+1 followed by a call with isign=-1 (or vice versa) returns the original data.

note the fact that the gridpoint values x(j) are real implies that b(0)=b(n/2)=0. for a call with isign=+1, it is not actually necessary to supply these zeros. note starting from grid with x(n)=x(n+1)=0 then transforming to spectral (sign=-1) then c(n/2)=a(n/2) is not necessarily 0 unless there is no aliasing.

#### **Parameters**

- a (ld\_a,\*) [real,inout] :: fields to be transformed
- ld\_a [integer,in,] :: leading dimension of a
- **n** [integer,in] :: dimension of problem
- **isign** [integer,in] :: back/forth transform for isign=1/-1
- **nsize** [integer,in] :: number of fields for
- wrk (wd1,wd2) [real,inout] :: work array
- wd1 [integer,in,]
- wd2 [integer,in,]
- i\_fft\_init (\*) [integer,in] :: factorization information from init\_fft
- **d\_fft\_init** (\*) [real,in] :: trigonometric functions from init\_fft

Called from fft thetab(), fft to real()

```
Call to fft99ajw(), wpass2jw(), wpass3jw(), wpass4jw(), wpass5jw(),
               fft99bjw()
subroutine fft_jw/fft99ajw(a, work, trigs, nrp, nsize)
           Parameters
                 • a (*) [real,inout]
                 • work (*) [real,inout]
                 • trigs (*) [real,in]
                 • nrp [integer,in]
                 • nsize [integer,in]
           Called from fftjw()
subroutine fft_jw/fft99bjw (work, a, trigsf, nrp, nsize)
           postprocessing step (isign=-1) (gridpoint to spectral transform)
           Parameters
                 • work (*) [real,inout]
                 • a (*) [real,inout]
                 • trigsf (*) [real,in]
                 • nrp [integer,in]
                 • nsize [integer,in]
          Called from fftjw()
subroutine fft_jw/wpass2jw (a, b, c, d, trigs, nrp, nsize)
          reduction for factor 2
          if(la /= 1) stop 'call to wpass2 with la /= 1'
          Parameters
                 • a (*) [real,in]
                 • b (*) [real,in]
                 • c (*) [real,out]
                 • d (*) [real,out]
                 • trigs (*) [real,in]
                 • nrp [integer,in]
                 • nsize [integer,in]
           Called from fftjw()
subroutine fft_jw/wpass3jw (a, b, c, d, trigs, nrp, la, nsize)
          called in fftJW
```

- **a** (\*) [real,in]
- **b** (\*) [real,in]
- **c** (\*) [real,out]
- **d** (\*) [real,out]
- **trigs** (\*) [real,in]
- **nrp** [integer,in]
- la [integer,in]
- **nsize** [integer,in]

Called from fftjw()

 $\textbf{subroutine} \ \texttt{fft\_jw/wpass4jw} \ (a,b,c,d,\textit{trigs},\textit{nrp},\textit{la},\textit{nsize})$ 

called in fftJW reduction for factor 4

#### **Parameters**

- **a** (\*) [real,in]
- **b** (\*) [real,in]
- **c** (\*) [real,out]
- **d** (\*) [real,out]
- **trigs** (\*) [real,in]
- **nrp** [integer,in]
- la [integer,in]
- **nsize** [integer,in]

Called from fftjw()

**subroutine** fft\_jw/wpass5jw (a, b, c, d, trigs, nrp, la, nsize)

called in fftJW reduction for factor 5

#### **Parameters**

- **a** (\*) [real,in]
- **b** (\*) [real,in]
- **c** (\*) [real,out]
- **d** (\*) [real,out]
- **trigs** (\*) [real,in]
- **nrp** [integer,in]
- la [integer,in]
- **nsize** [integer,in]

Called from fftjw()

## 10.12 Linear algebra

## 10.12.1 algebra.f90

#### **Quick access**

```
Variables zero_tolerance
Routines cgesl(), cgeslml(), sgesl(), sgefa()
```

### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- constants (one ()): module containing constants and parameters used in the code.
- omp\_lib

#### **Variables**

• algebra/zero\_tolerance [real,private/parameter=1.0e-15\_cp]

### **Subroutines and functions**

```
subroutine algebra/cgesl (a, ia, n, ip, bc1)
```

This routine does the backward substitution into a lu-decomposed real matrix a (to solve a \* x = bc1) were bc1 is the right hand side vector. On return x is stored in bc1.

## **Parameters**

- a (ia,\*) [real,in] :: real n X n matrix
- ia [integer,in,] :: first dim of a
- **n** [integer,in] :: dimension of problem
- ip (\*) [integer,in] :: pivot pointer of legth n
- **bc1** (\*) [complex,inout] :: on input RHS of problem

```
Called from j_cond(), updatez()
```

```
subroutine algebra/cgeslml (a, ia, n, ip, bc, ldbc, nrhss)
```

This routine does the backward substitution into a lu-decomposed real matrix a (to solve a \*x = bc) simultaneously for nRHSs complex vectors bc. On return the results are stored in the bc.

- a (ia,n) [real,in] :: real n X n matrix
- ia [integer,in,] :: leading dimension of a
- **n** [integer,in,] :: dimension of problem
- **ip** (n) [integer,in] :: pivot pointer of length n

- **bc** (ldbc,nrhss) [complex,inout] :: on input RHS of problem
- **Idbc** [integer,in,] :: leading dimension of bc
- nrhss [integer,in,] :: number of right-hand sides

Called from updates\_ala(), updateb(), updates(), updatewp(), updatez()

**subroutine** algebra/sgesl(a, ia, n, ip, b)

like the linpack routine backward substitution of vector b into lu-decomposed matrix a to solve a \* x = b for a single real vector b

sub sgefa must be called once first to initialize a and ip

a: (input) nxn real matrix n: (input) size of a and b ip: (input) pivot pointer array of length n b: (in/output) rhs-vector on input, solution on output

#### **Parameters**

- a (ia,\*) [real,in]
- ia [integer,in,] :: first dim of a
- **n** [integer,in] :: dim of problem
- **ip** (\*) [integer,in] :: pivot information
- **b** (\*) [real,inout]

Called from updates\_ala(), inits(), updates(), getbackground(), s\_cond()

**subroutine** algebra/**sgefa** (a, ia, n, ip, info)

like the linpack routine

lu decomposes the real matrix a(n,n) via gaussian elimination

a: (in/output) real nxn matrix on input, lu-decomposed matrix on output ia: (input) first dimension of a (must be >= n) n: (input) 2nd dimension and rank of a ip: (output) pivot pointer array info: (output) error message when /= 0

## **Parameters**

- **a** (ia,\*) [real,inout]
- ia [integer,in,]
- **n** [integer,in]
- **ip** (\*) [integer,out] :: pivoting information
- **info** [integer,out]

Called from get\_bmat(), inits(), get\_smat(), j\_cond(), getbackground(),
 get\_zmat(), s\_cond(), get\_z10mat(), get\_wpmat(), get\_s0mat()

## 10.13 Radial derivatives and integration

## 10.13.1 radial\_derivatives.f90

## **Description**

Radial derivatives functions

#### **Quick access**

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- cosine\_transform(costf1())
- constants (one (), three (), zero ()): module containing constants and parameters used in the code.

#### **Variables**

- radial\_der/get\_dr [public]
- radial\_der/get\_dcheb [public]

#### Subroutines and functions

Returns first radial derivative df of the input function f. Array  $f(n_f_max,*)$  may contain several functions numbered by the first index. The subroutine calculates the derivatives of the functions  $f(n_f_start,*)$  to  $f(n_f_stop)$  by transforming to a Chebychev representation using  $n_r_max$  radial grid points .

- **f** (n\_f\_max,\*) [complex,in]
- **df** (n\_f\_max,\*) [complex,out] :: first derivative of f
- n\_f\_max [integer,in,] :: first dim of f
- n\_f\_start [integer,in] :: first function to be treated
- **n\_f\_stop** [integer,in] :: last function to be treated
- n\_r\_max [integer,in] :: number of radial grid points
- n\_cheb\_max [integer,in] :: max number of cheb modes

- work1 (n\_f\_max,\*) [complex,out] :: work array needed for costf
- work2 (n\_f\_max,n\_r\_max) [complex,out] :: work array for f transfer
- i\_costf\_init (\*) [integer,in] :: info for costf
- **d\_costf\_init** (\*) [real,in] :: info for costf
- drx (\*) [real,in] :: first derivatives of x(r)

#### **Parameters**

- **f** (\*) [real,in]
- **df** (\*) [real,out] :: first derivative of f
- **n\_r\_max** [integer,in] :: number of radial grid points
- n\_cheb\_max [integer,in] :: max number of cheb modes
- work1 (\*) [real,out] :: work array needed for costf
- work2 (n\_r\_max) [real,out] :: work array for f transfer
- i\_costf\_init (\*) [integer,in] :: info for costf
- **d\_costf\_init** (\*) [real,in] :: info for costf
- **drx** (\*) [real,in] :: first derivatives of x(r)

Returns first radial derivative df of the input function f. Array  $f(n_f_max,^*)$  may contain several functions numbered by the first index. The subroutine calculates the derivatives of the functions  $f(n_f_start,^*)$  to  $f(n_f_stop,^*)$  by transforming to a Chebychev representation using  $n_r_max$  radial grid points. Note: when using this function the input field f is slightly changed by the back and forth transform. Use  $s_get_dr.f$  to avoid this.

#### **Parameters**

- **f** (n\_f\_max,\*) [complex,inout]
- **df** (n\_f\_max,\*) [complex,out] :: first derivative of f
- **n\_f\_max** [integer,in,] :: first dim of f
- **n\_f\_start** [integer,in] :: first function to be treated
- **n f stop** [integer,in] :: last function to be treated
- n\_r\_max [integer,in] :: number of radial grid points
- n\_cheb\_max [integer,in] :: max number of cheb modes
- work1 (n\_f\_max,\*) [complex,out] :: work array needed for costf
- i\_costf\_init (\*) [integer,in] :: info for costf
- **d\_costf\_init** (\*) [real,in] :: info for costf
- drx (\*) [real,in] :: first derivatives of x(r)

Called from dtbrms(), get\_dtblmfinish(), updates\_ala(), dtvrms(),
 updateb(), fields\_average(), write\_dtb\_frame(), updates()

Returns first radial derivative df and second radial derivative ddf of the input function f. Array  $f(n_f_max,^*)$  may contain several functions numbered by the first index. The subroutine calculates the derivatives of the functions  $f(n_f_start,^*)$  to  $f(n_f_start)$  by transforming to a Chebychev representation using  $n_f$  max radial grid points.

#### **Parameters**

- **f** (n f max,\*) [complex,in]
- **df** (n\_f\_max,\*) [complex,out] :: first derivative of f
- **ddf** (n\_f\_max,\*) [complex,out] :: second derivative of f
- n\_f\_max [integer,in,] :: first dim of f
- **n\_f\_start** [integer,in] :: first function to be treated
- n\_f\_stop [integer,in] :: last function to be treated
- n\_r\_max [integer,in] :: number of radial grid points
- **n\_cheb\_max** [integer,in] :: number of cheb modes
- work1 (n\_f\_max,\*) [complex,out] :: work array needed for costf
- work2 (n f max,\*) [complex,out] :: work array for f transfer
- i\_costf\_init (\*) [integer,in] :: info for costf
- **d\_costf\_init** (\*) [real,in] :: info for costf
- **drx** (\*) [real,in] :: first derivatives of x(r)
- **ddrx** (\*) [real,in] :: second derivatives of x(r)

```
Called from updates_ala(), getstartfields(), updateb(), updates(),
    updatez()
```

Call to get\_ddcheb()

Returns first radial derivative df, the second radial deriv. ddf, and the third radial derivative dddf of the input function f. Array  $f(n_f_max,^*)$  may contain several functions numbered by the first index. The subroutine calculates the derivatives of the functions  $f(n_f_start,^*)$  to  $f(n_f_stop)$  by transforming to a Chebychev representation using  $n_r_max$  radial grid points.

- **f** (n\_f\_max,\*) [complex,in]
- **df** (n f max,\*) [complex,out] :: first derivative of f
- **ddf** (n\_f\_max,\*) [complex,out] :: second derivative of f
- **dddf** (n\_f\_max,\*) [complex,out] :: third derivative of f
- n\_f\_max [integer,in,] :: first dim of f
- **n\_f\_start** [integer,in] :: first function to be treated
- **n\_f\_stop** [integer,in] :: last function to be treated

- n\_r\_max [integer,in] :: number of radial grid points
- n\_cheb\_max [integer,in] :: number of cheb\_modes
- work1 (n\_f\_max,\*) [complex,out] :: work array needed for costf
- work2 (n\_f\_max,\*) [complex,out] :: work array needed for costf
- i costf init (\*) [integer,in] :: info for costf
- **d costf init** (\*) [real,in] :: info for costf
- drx (\*) [real,in] :: first derivatives of x(r)
- **ddrx** (\*) [real,in] :: second derivatives of x(r)
- **dddrx** (\*) [real,in] :: third derivatives of x(r)

## Called from updatewp()

Call to get\_dddcheb()

#### **Parameters**

- **f** (n\_f\_max,\*) [complex,in]
- **df** (n\_f\_max,\*) [complex,out]
- n\_f\_max [integer,in,] :: Max no of functions
- **n\_f\_start** [integer,in] :: No of function to start with
- **n\_f\_stop** [integer,in] :: No of function to stop with
- n\_r\_max [integer,in] :: second dimension of f,df,ddf
- n\_cheb\_max [integer,in] :: Number of cheb modes
- **d\_fac** [real,in] :: factor for interval mapping

subroutine radial\_der/get\_dcheb\_real\_1d (f, df, n\_r\_max, n\_cheb\_max, d\_fac)

#### **Parameters**

- **f** (\*) [real,in]
- **df** (\*) [real,out]
- n\_r\_max [integer,in] :: second dimension of f,df,ddf
- n\_cheb\_max [integer,in] :: Number of cheb modes
- d fac [real,in]:: factor for interval mapping

Returns chebychev coefficients of first derivative df and second derivative ddf for a function whose cheb-coeff. are given as columns in array f(n\_c\_tot,n\_r\_max).

- **f** (n\_f\_max,\*) [complex,in]
- **df** (n\_f\_max,\*) [complex,out]
- **ddf** (n\_f\_max,\*) [complex,out]

- n\_f\_max [integer,in,] :: First dimension of f,df,ddf
- **n\_f\_start** [integer,in] :: No of column to start with
- **n\_f\_stop** [integer,in] :: No of column to stop with
- n\_r\_max [integer,in] :: second dimension of f,df,ddf
- n\_cheb\_max [integer,in] :: Number of cheb modes
- **d** fac [real,in] :: factor for interval mapping

Called from get\_ddr()

**subroutine** radial\_der/**get\_dddcheb** (f, df, ddf, ddf,  $n_f_max$ ,  $n_f_start$ ,  $n_f_stop$ ,  $n_r_max$ ,  $n_cheb_max$ ,  $d_fac$ )

#### **Parameters**

- **f** (n\_f\_max,\*) [complex,in]
- **df** (n\_f\_max,\*) [complex,out]
- **ddf** (n\_f\_max,\*) [complex,out]
- **dddf** (n\_f\_max,\*) [complex,out]
- n\_f\_max [integer,in,] :: First dimension of f,df,ddf
- n\_f\_start [integer,in] :: No of column to start with
- **n\_f\_stop** [integer,in] :: No of column to stop with
- n\_r\_max [integer,in] :: second dimension of f,df,ddf
- n\_cheb\_max [integer,in] :: Number of cheb modes
- **d\_fac** [real,in] :: factor for interval mapping

Called from get\_dddr()

## 10.13.2 radial derivatives even.f90

## **Quick access**

```
Routines get_ddcheb_even(), get_ddr_even(), get_dcheb_even(), get_ddrns_even()
```

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- cosine\_transform(costf2(), costf1())
- constants (zero ()): module containing constants and parameters used in the code.

#### **Variables**

#### **Subroutines and functions**

Returns first rarial derivative df and second radial derivative ddf of the input function f. Array  $f(n_f_max,*)$  may contain several functions numbered by the first index. The subroutine calculates the derivatives of the functions  $f(n_f_start,*)$  to  $f(n_f_stop)$  by transforming to a Chebychev representation using  $n_r_max$  radial grid points. The cheb transforms have to be initialized by calling init costf1 and init costf2.

#### **Parameters**

- **f** (n\_f\_max,\*) [complex,in]
- **df** (n\_f\_max,\*) [complex,out] :: first derivative of f
- **ddf** (n\_f\_max,\*) [complex,out] :: second derivative of f
- **n\_f\_max** [integer,in,] :: first dim of f
- **n\_f\_start** [integer,in] :: first function to be treated
- **n\_f\_stop** [integer,in] :: last function to be treated
- n\_r\_max [integer,in] :: number of radial grid points
- n cheb max [integer,in] :: number of cheb modes
- **dr\_fac** [real,in] :: mapping factor
- work1 (n\_f\_max,\*) [complex,out] :: work array needed for costf
- work2 (n\_f\_max,\*) [complex,out] :: work array needed for costf
- i\_costf1\_init (\*) [integer,in]
- d\_costf1\_init (\*) [real,in]
- i\_costf2\_init (\*) [integer,in]
- **d\_costf2\_init** (\*) [real,in]

**Called from** getstartfields(), updateb()

Call to get\_ddcheb\_even(), costf2()

Returns first rarial derivative df and second radial derivative ddf of the input function f. Array  $f(n_f_max,*)$  may contain several functions numbered by the first index. The subroutine calculates the derivatives of the functions  $f(n_f_start,*)$  to  $f(n_f_stop)$  by transforming to a Chebychev representation using  $n_r_max$  radial grid points. The cheb transforms have to be initialized by calling init\_costf1 and init\_costf2.

#### **Parameters**

• **f** (n\_f\_max,\*) [complex,inout]

```
df (n_f_max,*) [complex,out] :: first derivative of f
n_f_max [integer,in,] :: first dim of f
n_f_start [integer,in] :: first function to be treated
n_f_stop [integer,in] :: last function to be treated
n_r_max [integer,in] :: number of radial grid points
n_cheb_max [integer,in] :: number of cheb modes
dr_fac [real,in] :: mapping factor
work1 (n_f_max,*) [complex,out] :: work array needed for costf
i_costf1_init (*) [integer,in]
d_costf1_init (*) [integer,in]
d_costf2_init (*) [integer,in]
d_costf2_init (*) [real,in]

Called from fields_average(), write_dtb_frame()
```

**subroutine** radial\_der\_even/**get\_ddrns\_even** (f, df, ddf,  $n\_f\_max$ ,  $n\_f\_start$ ,  $n\_f\_stop$ ,  $n\_r\_max$ ,  $n\_cheb\_max$ ,  $dr\_fac$ , work1,  $i\_costf1\_init$ ,  $d\_costf1\_init$ ,  $i\_costf2\_init$ ,  $d\_costf2\_init$ 

Returns first rarial derivative df and second radial derivative ddf of the input function f. Array  $f(n_f_max,^*)$  may contain several functions numbered by the first index. The subroutine calculates the derivatives of the functions  $f(n_f_start,^*)$  to  $f(n_f_stop)$  by transforming to a Chebychev representation using  $n_r_max$  radial grid points. The cheb transforms have to be initialized by calling init\_costf1 and init\_costf2.

### **Parameters**

• **f** (n\_f\_max,\*) [complex,inout]

Call to get dcheb even(), costf2()

- **df** (n\_f\_max,\*) [complex,out] :: first derivative of f
- **ddf** (n\_f\_max,\*) [complex,out] :: second derivative of f
- **n\_f\_max** [integer,in,] :: first dim of f
- **n f start** [integer,in] :: first function to be treated
- **n\_f\_stop** [integer,in] :: last function to be treated
- **n\_r\_max** [integer,in] :: number of radial grid points
- n\_cheb\_max [integer,in] :: number of cheb modes
- **dr\_fac** [real,in] :: mapping factor
- work1 (n\_f\_max,\*) [complex,out] :: work array needed for costf
- i\_costf1\_init (\*) [integer,in]
- **d\_costf1\_init** (\*) [real,in]
- i\_costf2\_init (\*) [integer,in]
- **d\_costf2\_init** (\*) [real,in]

Called from fields average()

```
Call to get_ddcheb_even(), costf2()
```

**subroutine** radial\_der\_even/**get\_dcheb\_even** (f, df,  $n\_f\_max$ ,  $n\_f\_start$ ,  $n\_f\_stop$ ,  $n\_r\_max$ ,  $n\_cheb\_max$ ,  $d\_fac$ )

#### **Parameters**

- **f** (n\_f\_max,\*) [complex,in]
- **df** (n f max,\*) [complex,out]
- **n\_f\_max** [integer,in,] :: First dimension of f,df
- **n\_f\_start** [integer,in] :: No of function to start with
- **n\_f\_stop** [integer,in] :: No of function to stop with
- n\_r\_max [integer,in] :: second dimension of f,df
- **n\_cheb\_max** [integer,in] :: Number of cheb modes
- **d\_fac** [real,in] :: factor for interval mapping

Called from get\_drns\_even()

#### **Parameters**

- **f** (n\_f\_max,\*) [complex,in]
- **df** (n\_f\_max,\*) [complex,out]
- **ddf** (n\_f\_max,\*) [complex,out]
- **n\_f\_max** [integer,in,] :: First dimension of f,df,ddf
- **n\_f\_start** [integer,in] :: No of function to start with
- **n\_f\_stop** [integer,in] :: No of function to stop with
- n\_r\_max [integer,in] :: second dimension of f,df,ddf
- n\_cheb\_max [integer,in] :: Number of cheb modes
- **d\_fac** [real,in] :: factor for interval mapping

Called from get\_ddr\_even(), get\_ddrns\_even()

## **10.13.3** integration.f90

## **Description**

Radial integration functions

#### **Quick access**

Routines rint\_r(), rintic(), rint()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- cosine\_transform(costf1())
- constants (one (), half (), two ()): module containing constants and parameters used in the code.

#### **Variables**

#### Subroutines and functions

**function** integration/**rint** (*f*, *nrmax*, *drfac*, *i\_costf\_init*, *d\_costf\_init*)

This function performs the radial integral over a function f that is given on the appropriate nRmax radial Chebychev grid points. The arrays i\_costf\_init,d\_costf\_init are defined by calling init\_costf1.

**Note:** drFac maps radius to cheb space [-1,1] drFac=two/(rMax-rMin)

#### **Parameters**

- **f** (\*) [real,in]
- **nrmax** [integer,in]
- **drfac** [real,in]
- i\_costf\_init (\*) [integer,in]
- d\_costf\_init (\*) [real,in]

**Return rint** [real]

```
Called from outperppar(), outmisc(), spectrum_temp_average(),
    spectrum_temp()
```

function integration/rintic(f, nrmax, drfac, i\_costf\_init, d\_costf\_init)

This function performs the radial integral over a function f that is given on the appropriate nRmax radial Chebychev grid points. The arrays i\_costf\_init,d\_costf\_init are defined by calling init\_costf1.

## **Parameters**

- **f** (\*) [real,inout]
- nrmax [integer,in]
- **drfac** [real,in]
- i\_costf\_init (\*) [integer,in]
- d\_costf\_init (\*) [real,in]

**Return rintic** [real]

```
Called from get_power(), get_e_mag(), spectrum()
```

**function** integration/**rint\_r**(*f*, *n\_r\_max*, *n\_cheb\_max*, *dr\_fac*, *i\_costf\_init*, *d\_costf\_init*)

#### **Parameters**

• **f** (\*) [real,in]

- n\_r\_max [integer,in]
- n\_cheb\_max [integer,in]
- **dr\_fac** (\*) [real,in]
- i\_costf\_init (\*) [integer,in]
- d\_costf\_init (\*) [real,in]

## Return rint r [real]

```
Called from outto(), dtbrms(), output(), dtvrms(), get_angular_moment(),
    get_poltorrms(), get_power(), get_e_mag(), spectrum(), precalc(),
    get_e_kin(), getdlm(), spectrum_average(), get_u_square()
```

# 10.14 Blocking and LM mapping

## 10.14.1 blocking.f90

### Description

Module containing blocking information

#### **Quick access**

Variables nbsave, nbdown, sizethetabi, cacheblock\_size\_in\_b, lm22lm, lmp2lmpa, lm2, lm2lmp, lmp2lm, lm2l, sizelmb2, lm2mc, lmstartb, nlmbs2, lmp2, lm2m, lm22l, lm2lms, lm2lma, l2lmas, lm22m, lmp2l, lmp2lmps, lmstopb, get\_theta\_blocking, sn\_sub\_map, lo\_sub\_map, st\_map, st\_sub\_map, lo\_map, sizelmb, sizerb, nlmbs, nfs, nthetabs, sizethetab

```
Routines initialize_blocking(), get_theta_blocking_cache(), get_subblocks(), get_lorder_lm_blocking(), get_standard_lm_blocking(), get_theta_blocking_openmp(), get_snake_lm_blocking()
```

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- lmmapping (mappings(), subblocks\_mappings(), allocate\_subblocks\_mappings(),
  allocate\_mappings())
- output\_data(nlf(), log\_file()): This module contains the parameters for output control
- logic (1 save out ()): Module containing the logicals that control the run
- useful (logwrite()): library with several useful subroutines
- truncation(lm\_max(), n\_r\_max(), minc(), lmp\_max(), l\_max(), nrp(), n\_theta\_max()): This module defines the grid points and the truncation
- parallel\_mod(nthreads(), n\_procs(), rank\_with\_l1m0(), rank(), nlmbs\_per\_rank()): This module contains the blocking information

#### **Variables**

- blocking/sn\_sub\_map[subblocks\_mappings,target/public]
- blocking/lm2lma (:) [integer, pointer/public]
- blocking/lmp2 (:,:) [integer,pointer/public]
- blocking/lm2mc(:)[integer,pointer/public]
- blocking/lmstopb(:)[integer,allocatable/public]
- blocking/**nbsave** [integer,private/parameter=16]
- blocking/lo\_map [mappings,target/public]
- blocking/**nfs** [integer,public]
- blocking/lm22lm(:,:,:) [integer,pointer/public]
- blocking/lm2 (:,:) [integer,pointer/public]
- blocking/sizerb[integer,public]
- blocking/sizethetabi[integer,private/parameter=284]
- blocking/st\_map [mappings,target/public]
- blocking/st\_sub\_map[subblocks\_mappings,target/public]
- blocking/sizelmb2 (:,:) [integer,pointer/public]
- blocking/lmstartb(:)[integer,allocatable/public]
- blocking/sizethetab[integer,public]
- blocking/lm2lmp(:)[integer,pointer/public]
- blocking/lm2m(:) [integer, pointer/public]
- blocking/lmp21 (:) [integer, pointer/public]
- blocking/lmp2lmps (:) [integer,pointer/public]
- blocking/sizelmb[integer,public]
- blocking/cacheblock\_size\_in\_b[integer,public]
- blocking/nthetabs[integer,public]
- blocking/nlmbs2 (:) [integer, pointer/public]
- blocking/lmp2lmpa (:) [integer, pointer/public]
- blocking/121mas (:) [integer, pointer/public]
- blocking/get\_theta\_blocking[public]
- blocking/lm2lms (:) [integer, pointer/public]
- blocking/nlmbs[integer,public]
- blocking/lm22m(:,:,:) [integer,pointer/public]
- blocking/lmp2lm(:)[integer,pointer/public]
- blocking/lm21(:)[integer,pointer/public]
- blocking/lm221 (:,:,:) [integer,pointer/public]
- blocking/nbdown [integer,private/parameter=8]

• blocking/lo\_sub\_map [subblocks\_mappings,target/public]

## **Subroutines and functions**

```
subroutine blocking/initialize_blocking()
```

#### Called from magic

subroutine blocking/get\_subblocks (map, sub\_map)

#### **Parameters**

- map [mappings,in]
- **sub\_map** [subblocks\_mappings,inout]

Called from initialize blocking()

subroutine blocking/get\_standard\_lm\_blocking(map, minc)

#### **Parameters**

- map [mappings,inout]
- minc [integer,in]

Called from initialize\_blocking()

subroutine blocking/get\_lorder\_lm\_blocking (map, minc)

#### **Parameters**

- map [mappings,inout]
- minc [integer,in]

Called from initialize\_blocking()

subroutine blocking/get snake lm blocking(map, minc)

#### **Parameters**

- map [mappings,inout]
- minc [integer,in]

Called from initialize\_blocking()

- n\_theta\_max [integer,in]
- **nrp** [integer,in]
- cacheblock\_size\_in\_b [integer,in]
- **nthetabs** [integer,out]
- sizethetab [integer,out]

```
Called from initialize_blocking()
```

**subroutine** blocking/**get\_theta\_blocking\_openmp** (*n\_theta\_max*, *nthreads*, *nthetabs*, *sizethetab*)

This routine determines the number of theta blocks and the blocksize with respect to the number of threads.

#### **Parameters**

- n\_theta\_max [integer,in]
- **nthreads** [integer,in]
- **nthetabs** [integer,out]
- sizethetab [integer,out]

Called from initialize\_blocking()

## 10.14.2 LMmapping.f90

#### **Quick access**

**Routines** allocate\_subblocks\_mappings(), allocate\_mappings()

### **Types**

• type lmmapping/unknown\_type

## Type fields

- % lm2lma (\*) [integer, allocatable]
- % lmp2 (,) [integer, allocatable]
- % lm2mc (\*) [integer, allocatable]
- % lmp2lmpa (\*) [integer,allocatable]
- % lmp\_max [integer]
- % lm2 (,) [integer, allocatable]
- % lm2lms (\*) [integer, allocatable]
- % 121mas (\*) [integer, allocatable]
- % lmp21 (\*) [integer, allocatable]
- % lm2lmp (\*) [integer,allocatable]
- % lm\_max [integer]
- % lm2m(\*)[integer,allocatable]
- % lmp2lm (\*) [integer, allocatable]
- % lm21 (\*) [integer,allocatable]
- % 1\_max [integer]
- % lmp2lmps (\*) [integer, allocatable]
- type lmmapping/unknown\_type

## Type fields

- % sizelmb2 (,) [integer, allocatable]
- % nlmbs [integer]
- % nlmbs2 (\*) [integer, allocatable]
- % lm22m (,,\*) [integer, allocatable]
- % sizelmb2max [integer]
- % 1\_max [integer]
- % lm221 (,,\*) [integer, allocatable]
- % lm22lm (,,\*) [integer,allocatable]

#### **Variables**

#### Subroutines and functions

subroutine lmmapping/allocate\_mappings (self, l\_max, lm\_max, lmp\_max)

## **Parameters**

- self [mappings]
- l\_max [integer,in]
- lm\_max [integer,in]
- lmp\_max [integer,in]

Called from initialize\_blocking()

subroutine lmmapping/allocate\_subblocks\_mappings (self, map, nlmbs, l\_max, lmstartb, lmstopb)

#### **Parameters**

- **self** [subblocks\_mappings]
- map [mappings,in]
- nlmbs [integer,in,]
- l\_max [integer,in]
- **Imstartb** (*nlmbs*) [integer,in]
- **lmstopb** (*nlmbs*) [integer,in]

Called from initialize\_blocking()

# 10.15 IO: time series, radial profiles and spectra

## 10.15.1 output.f90

### **Quick access**

Variables n\_t\_r\_sets, n\_v\_r\_sets, n\_b\_r\_sets, dipcmbmean, elcmbmean, dlvcmean, timenormlog, geosmean, rolmean, lbdissmean, e\_kin\_pmean, rmmean, e\_kin\_tmean, dteint, etot, dzvmean, dmbmean, dipmean, dpvmean, elmean, dmvmean, timepassedlog, dlvmean, e\_mag\_pmean, e\_mag\_tmean, dlbmean, lvdissmean, etotold, ntpotsets, n\_cmb\_setsmov, n\_dt\_cmb\_sets, ntosets, nrms\_sets, ntomovsets, nbpotsets, ntormssets, n\_spec, nvpotsets, n\_e\_sets, npvsets, nlogs

Routines output(), initialize\_output()

#### **Needed modules**

- storecheckpoints: This module contains several subroutines that can be used to store the rst\_#.TAG files
- physical\_parameters (nvarcond(), prmag(), lffac(), opm(), ek(), ktopv()): Module containing the physical parameters
- output\_data (cmbmov\_file(), dt\_cmb\_file(), n\_r\_array(), cmb\_file(), n\_cmbmov\_file(), n\_coeff\_r(), n\_cmb\_file(), l\_max\_cmb(), n\_t\_r\_file(), n\_rst\_file(), n
- constants (vol\_oc(), surf\_cmb(), two(), mass(), vol\_ic()): module containing constants and parameters used in the code.
- blocking (st\_map(), lo\_map(), lm2()): Module containing blocking information
- useful (safeopen(), safeclose(), logwrite()): library with several useful subroutines
- fields (p(), ddw\_lmloc(), s(), db(), ddj\_lmloc(), aj\_ic\_lmloc(), ddw(), ddj\_ic(), b\_lmloc(), ddb\_ic\_lmloc(), ds\_lmloc(), omega\_ma(), ddb\_lmloc(), p\_lmloc(), omega\_ic(), ds(), dj\_lmloc(), dj(), dz(), aj(), db\_lmloc(), ddb\_ic(), aj\_lmloc(), z\_lmloc(), b(), b\_ic(), z(), dw\_lmloc(), dz\_lmloc(), w(), db\_ic\_lmloc(), dj\_ic(), ddj(), dj\_ic\_lmloc(), b\_ic\_lmloc(), ddj\_ic\_lmloc(), w\_lmloc(), dw(), db\_ic(), s\_lmloc(), aj\_ic(), ddb()): This module contains the potential fields and their radial derivatives
- movie\_data(movie\_gather\_frames\_to\_rank0())
- truncation (l\_maxmag(), lm\_max(), n\_r\_max(), minc(), l\_max(), n\_r\_maxmag(), n\_r\_ic\_max()): This module defines the grid points and the truncation
- spectra (spectrum\_temp(), spectrum\_temp\_average(), spectrum\_average(), spectrum())
- integration (rint\_r()): Radial integration functions
- parallel\_mod (rank ()): This module contains the blocking information
- omega (outomega ()): This module allows to compute the axisymmetric zonal flow versus the cylindrical radius s. By

- out\_movie\_ic(store\_movie\_frame\_ic())
- magnetic\_energy (get\_e\_mag())
- radial\_spectra
- out\_coeff (write\_bcmb(), write\_coeff\_r()): This module contains the subroutines that calculate the Bcmb files and the [BIVIT]\_coeff\_r files
- power (get\_power ())
- communications(gt\_ic(), gather\_all\_from\_lo\_to\_rank0(), gt\_oc())
- outpar\_mod(outperppar(), outpar())
- kinetic\_energy (get\_u\_square(), get\_e\_kin())
- rms (zerorms ()): This module contains the global array used when RMS force balance is requested
- precision\_mod: This module controls the precision used in MagIC
- outmisc\_mod(outmisc())
- horizontal\_data (dlh(), dpl0eq(), hdif\_b()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_non\_rot(), l\_store\_frame(), l\_sric(), lverbose(), l\_r\_fieldt(), l\_cmb\_field(), l\_cond\_ic(), l\_average(), l\_perppar(), l\_power(), l\_save\_out(), l\_rmagspec(), l\_r\_field(), l\_dt\_cmb\_field(), l\_anel(), l\_dtb(), l\_mag(), l\_pv(), l\_rms(), l\_mag\_lf(), l\_movie\_ic()): Module containing the logicals that control the run
- getdlm\_mod(getdlm())
- radial\_functions (drx(), r\_cmb(), or1(), d\_costf\_init(), or2(), i\_costf\_init(), r\_icb(), r())
- fields\_average\_mod (fields\_average()): This module is used when one wants to store time-averaged quantities
- radial\_data(nrstop(), n\_r\_cmb(), nrstopmag(), nrstartmag(), nrstart())
- outto\_mod(outto())
- dtb\_mod(get\_dtblmfinish()): This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output....
- charmanip (dble2str()): This module contains several useful routines to manipule character strings
- lmloop\_data(ulm(), lm\_per\_rank(), llmmag(), ulmmag(), llm(), lm\_on\_last\_rank())
- graphout mod (graphout ic())
- outrot (write\_rot())
- fieldslast (djdt\_iclast\_lmloc(), djdtlast\_lmloc(), dsdtlast\_lmloc(), dzdtlast\_lo(), dzdtlast(), djdtlast(), dwdtlast\_lmloc(), dbdt\_iclast\_lmloc(), dpdtlast\_lmloc(), dwdtlast(), dsdtlast(), djdt\_iclast(), dpdtlast(), dbdtlast\_lmloc(), dbdt\_iclast(), dbdtlast()): This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- out\_movie(write\_movie\_frame())
- num\_param(tscale()): Module containing numerical and control parameters
- outpv3(outpv())
- out\_rms(dtvrms(), dtbrms())

• store\_pot\_mod (storepot ()): This module contains the subroutines that can be used to write unformatted fortran files that contain the flow/magnetic field potentials (in both Chebyshev and spectral space)

#### **Variables**

- output\_mod/n\_cmb\_setsmov[integer,private]
- output\_mod/npvsets[integer,private]
- output\_mod/timenormlog[real,private]
- output\_mod/e\_mag\_tmean [real,private]
- output\_mod/ntormssets[integer,private]
- output\_mod/dlbmean [real,private/save]
- output\_mod/ntpotsets [integer,private]
- output\_mod/dteint [real,private]
- output\_mod/ntosets[integer,private]
- output\_mod/e\_kin\_pmean [real,private]
- output\_mod/elcmbmean [real,private/save]
- output\_mod/n\_e\_sets[integer,private]
- output\_mod/dmvmean [real,private/save]
- output\_mod/dipcmbmean [real,private/save]
- output\_mod/geosmean [real,private/save]
- output\_mod/lvdissmean [real,private/save]
- output\_mod/elmean [real,private/save]
- output\_mod/ntomovsets[integer,private]
- output\_mod/rmmean [real,private/save]
- output\_mod/n\_spec [integer,private]
- output mod/dmbmean [real,private/save]
- output\_mod/etot [real,private]
- output\_mod/nbpotsets[integer,private]
- output\_mod/lbdissmean [real,private/save]
- output\_mod/rolmean [real,private/save]
- output\_mod/dlvmean [real,private/save]
- output\_mod/n\_t\_r\_sets(:)[integer,private/allocatable]
- output\_mod/e\_mag\_pmean [real,private]
- output mod/dzvmean [real, private/save]
- output\_mod/timepassedlog[real,private]
- output\_mod/nvpotsets [integer,private]
- output\_mod/nrms\_sets [integer,private]

- output\_mod/e\_kin\_tmean [real,private]
- output\_mod/dipmean [real,private/save]
- output\_mod/etotold[real,private]
- output\_mod/n\_b\_r\_sets(:)[integer,private/allocatable]
- output\_mod/nlogs [integer,private]
- output\_mod/n\_dt\_cmb\_sets[integer,private]
- output\_mod/n\_v\_r\_sets (:) [integer,private/allocatable]
- output\_mod/**dpvmean** [real,private/save]
- output\_mod/dlvcmean [real,private/save]

#### **Subroutines and functions**

```
subroutine output_mod/initialize_output()
```

Called from magic

subroutine output\_mod/output (time, dt, dtnew, n\_time\_step, l\_stop\_time, l\_bpot, l\_vpot, l\_tpot, l\_log, l\_graph, lrmscalc, l\_store, l\_new\_rst\_file, l\_spectrum, ltocalc, ltoframe, ltozwrite, l\_frame, n\_frame, l\_cmb, n\_cmb\_sets, l\_r, lorentz\_torque\_ic, lorentz\_torque\_ma, dbdt\_at\_cmb, hellmr, hel2lmr, helnalmr, helna2lmr, uhlmr, duhlmr, gradslmr, fconvlmr, fkinlmr, fvisclmr, fpoynlmr, freslmr, eperplmr, eparlmr, eperpaxilmr, eparaxilmr)

This subroutine controls most of the output.

- time [real,in]
- **dt** [real,in]
- dtnew [real,in]
- n\_time\_step [integer,in]
- l\_stop\_time [logical,in]
- **l\_bpot** [logical,in]
- **l\_vpot** [logical,in]
- l\_tpot [logical,in]
- l\_log [logical,in]
- l\_graph [logical,in]
- **Irmscalc** [logical,in]
- **l\_store** [logical,in]
- l\_new\_rst\_file [logical,in]
- l\_spectrum [logical,in]
- **ltocalc** [logical,in]
- **Itoframe** [logical,in]

- **ltozwrite** [logical,inout]
- **l\_frame** [logical,in]
- n\_frame [integer,inout]
- l\_cmb [logical,in]
- n\_cmb\_sets [integer,inout]
- l r [logical,in]
- lorentz\_torque\_ic [real,in]
- lorentz\_torque\_ma [real,in]
- **dbdt\_at\_cmb** (\*) [complex,in,pointer]
- **hellmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **hel2lmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **helnalmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- helna2lmr (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **uhlmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real,in*]
- **duhlmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- gradslmr (l\_max+1,nrstop-(nrstart)+1) [real,in]
- **fconvlmr** (*l max*+1,*nrstop*-(*nrstart*)+1) [real,in]
- **fkinlmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **fvisclmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **fpoynlmr** (*l\_maxmag+1,nrstopmag-(nrstartmag)+1*) [real,in]
- **freslmr** (*l\_maxmag*+1,*nrstopmag*-(*nrstartmag*)+1) [*real,in*]
- **eperplmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **eparlmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **eperpaxilmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **eparaxilmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]

## Called from step\_time()

```
Call to write_rot(), get_e_kin(), get_e_mag(), spectrum_average(),
    spectrum_temp_average(), fields_average(), get_power(),
    get_u_square(), outperppar(), getdlm(), outpar(), outmisc(),
    spectrum(), spectrum_temp(), outto(), get_dtblmfinish(),
    zerorms(), dtvrms(), dtbrms(), gather_all_from_lo_to_rank0(),
    movie_gather_frames_to_rank0(), graphout_ic(), rbrspec(),
    rbpspec(), store_movie_frame_ic(), logwrite(), write_movie_frame(),
    write_bcmb(), write_coeff_r(), rint_r(), safeopen(), safeclose(),
    storepot(), dble2str(), store(), outomega(), outpv()
```

## 10.15.2 kinetic\_energy.f90

#### **Quick access**

Routines initialize\_kinetic\_energy(), get\_e\_kin(), get\_u\_square()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (nvarcond(), ek(), prmag()): Module containing the physical parameters
- horizontal\_data(dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_save\_out(), l\_non\_rot()): Module containing the logicals that control the run
- radial\_functions (orho2(), drx(), r\_cmb(), or1(), d\_costf\_init(), or2(), i\_costf\_init(), r\_icb(), r(), sigma(), orho1())
- blocking (st\_map(), lo\_map()): Module containing blocking information
- useful (cc2real ()): library with several useful subroutines
- truncation (n\_r\_max(), l\_max()): This module defines the grid points and the truncation
- communications (get\_global\_sum())
- integration (rint\_r()): Radial integration functions
- parallel\_mod: This module contains the blocking information
- output\_data (n\_e\_kin\_file(), u\_square\_file(), tag(), n\_u\_square\_file(), e\_kin\_file()): This module contains the parameters for output control
- constants (vol\_oc(), two(), pi(), one(), half(), four()): module containing constants and parameters used in the code.
- num\_param(tscale(), escale()): Module containing numerical and control parameters
- lmloop\_data(ulm(), llm())

#### **Variables**

- kinetic\_energy/e\_p\_asa(:) [real,private/allocatable]
- kinetic\_energy/e\_t\_asa(:)[real,private/allocatable]
- kinetic\_energy/e\_ta(:)[real,private/allocatable]
- kinetic\_energy/e\_pa(:)[real,private/allocatable]

## **Subroutines and functions**

#### **Parameters**

- **time** [real,in] :: Current time
- **l\_write** [logical,in] :: Switch to write output
- **l\_stop\_time** [logical,in] :: Indicates when last time step of the run is reached for radial output
- n\_e\_sets [integer,in] :: Switch for time-average and to determine first time step
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **e\_p** [real,out] :: poloidal energy
- e\_t [real,out] :: toroidal energy
- **e\_p\_as** [real,out] :: axisymmetric poloidal energy
- e\_t\_as [real,out] :: axisymmetric toroidal energy

**Options** ekinr (*n\_r\_max*) [real,out,optional] :: Radial profile of kinetic energy

```
Called from output(), fields_average()
```

Call to cc2real(), rint\_r()

subroutine kinetic\_energy/get\_u\_square (time, w, dw, z, rolr, dlr, dlrc)

calculates square velocity = 1/2 Integral ( $v^2 dV$ ) integration in theta,phi by summation of spherical harmonics integration in r by using Chebychef integrals

Write the different contributions in u\_square.TAG file

#### **Parameters**

- time [real,in] :: Current time
- $\mathbf{w}$  (ulm-(llm)+1,n\_r\_max) [complex,in]
- $\mathbf{dw}$  (ulm-(llm)+1,n\_r\_max) [complex,in]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- rolr (n\_r\_max) [real,out] :: local Rossby number
- **dlr** (*n\_r\_max*) [real,out] :: Length scale
- **dlrc** (n r max) [real,out] :: Convective length scale

Called from output ()

Call to cc2real(), rint\_r()

## 10.15.3 magnetic\_energy.f90

#### Quick access

```
Variables e_pa, e_p_asa, e_dipa, e_t_asa, e_ta
Routines initialize_magnetic_energy(), get_e_mag()
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (ktopb(), kbotb(), 1ffac()): Module containing the physical parameters
- horizontal\_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_mag(), l\_save\_out(), l\_mag\_lf(), l\_cond\_ic()): Module containing the logicals that control the run
- radial\_functions (r\_ic(), d\_costf\_init(), r\_cmb(), or2(), i\_costf\_init(), d\_costfl\_ic\_init(), i\_costfl\_ic\_init(), drx(), orhol(), dr\_fac\_ic(), sigma(), r\_icb(), r())
- blocking (st\_map(), lmstartb(), lo\_map(), lmstopb()): Module containing blocking information
- useful (cc22real (), cc2real ()): library with several useful subroutines
- radial\_data(n\_r\_cmb())
- movie\_data (moviediplon(), moviedipstrengthgeo(), moviedipcolat(), moviedipstrength())
- truncation (n\_r\_max(), n\_r\_maxmag(), n\_r\_ic\_maxmag(), n\_r\_ic\_max()): This module defines the grid points and the truncation
- integration(rint\_r(), rintic()): Radial integration functions
- parallel mod: This module contains the blocking information
- output\_data (dipole\_file(), tag(), n\_dipole\_file(), n\_e\_mag\_oc\_file(), e\_mag\_ic\_file(), n\_e\_mag\_ic\_file(), e\_mag\_oc\_file()): This module contains the parameters for output control
- constants (two(), pi(), one(), half(), zero(), four()): module containing constants and parameters used in the code.
- num\_param(tscale(), escale()): Module containing numerical and control parameters
- lmloop\_data(llmmag(), ulmmag())
- bext (n\_imp(), rrmp()): Module containing the external field parameters

## **Variables**

- magnetic\_energy/e\_p\_asa(:) [real,private/allocatable]
- magnetic\_energy/e\_t\_asa(:)[real,private/allocatable]
- magnetic\_energy/e\_ta(:) [real,private/allocatable]
- $\bullet \ \texttt{magnetic\_energy/e\_pa} \ (:) \ \textit{[real,private/allocatable]}$
- magnetic\_energy/e\_dipa(:)[real,private/allocatable]

## **Subroutines and functions**

subroutine magnetic\_energy/initialize\_magnetic\_energy()

#### Called from magic

calculates magnetic energy = 1/2 Integral(B<sup>2</sup> dV) integration in theta,phi by summation over harmonic coeffs. integration in r by Chebycheff integrals

- **time** [real,in] :: Current time
- **l\_write** [logical,in] :: Switch to write output
- **l\_stop\_time** [logical,in] :: Indicates when last time step of the run is reached for radial output
- n\_e\_sets [integer,in] :: Switch for time-average and to determine first time step
- **b** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **db** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **aj** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [*complex,in*]
- **b\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- **db\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- aj\_ic (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- **e\_p** [real,out] :: Volume averaged poloidal magnetic energy
- **e\_t** [real,out] :: Volume averaged toroidal magnetic energy
- e\_p\_as [real,out] :: Volume averaged axisymmetric poloidal magnetic energy
- e\_t\_as [real,out] :: Volume averaged axisymmetric toroidal magnetic energy
- **e\_p\_ic** [real,out] :: IC poloidal magnetic energy
- e\_t\_ic [real,out] :: IC toroidal magnetic energy
- e\_p\_as\_ic [real,out] :: IC axisymmetric poloidal magnetic energy
- **e\_t\_as\_ic** [real,out] :: IC axisymmetric toroidal magnetic energy
- **e\_p\_os** [real,out] :: Outside poloidal magnetic energy
- e\_p\_as\_os [real,out] :: Outside axisymmetric poloidal magnetic energy
- e\_cmb [real,out] :: Magnetic energy at the CMB
- **dip** [real,out]:: Relative magnetic energy of axial dipole
- **dipcmb** [real,out]:: Relative magnetic energy of axial dipole at the CMB
- elsanel [real,out] :: Radially averaged Elsasser number

```
Called from output(), fields_average()
Call to cc2real(), rint r(), cc22real(), rintic()
```

## 10.15.4 getDlm.f90

#### **Quick access**

Routines getdlm()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- horizontal\_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- constants (half(), pi()): module containing constants and parameters used in the code.
- radial\_functions(drx(), or2(), i\_costf\_init(), orho1(), d\_costf\_init())
- blocking (st\_map(), lo\_map()): Module containing blocking information
- useful (cc22real (), cc2real ()): library with several useful subroutines
- num\_param (escale()): Module containing numerical and control parameters
- lmloop\_data(ulm(), llm())
- truncation (m\_max(), n\_r\_max(), l\_max(), minc()): This module defines the grid points and the truncation
- integration (rint\_r()): Radial integration functions
- parallel\_mod: This module contains the blocking information

#### **Variables**

## **Subroutines and functions**

**subroutine** getdlm\_mod/**getdlm** (w, dw, z, dl, dlr, dm, dlc, dlrc, switch\_bn)

calculates energy = 1/2 Integral(B<sup>2</sup> dV) integration in theta,phi by summation over harmonic coeffs. integration in r by Chebycheff integrals

Output: enbp: Total poloidal enbt: Total toroidal apome: Axisym. poloidal atome: Axisym. toroidal

- $\mathbf{w}$  (ulm-(llm)+1,n\_r\_max) [complex,in]
- **dw** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dl** [real,out]
- **dlr** (*n\_r\_max*) [*real,out*]
- dm [real,out]
- dlc [real,out]
- **dlrc** (*n\_r\_max*) [real,out]
- switch\_bn [character,in]

```
Called from output()
Call to cc2real(), rint r()
```

#### 10.15.5 outMisc.f90

#### **Quick access**

Routines outmisc()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (epss ()): Module containing the physical parameters
- legendre\_spec\_to\_grid(lmas2pt())
- horizontal\_data(gauss()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_save\_out(), l\_anelastic\_liquid(), l\_hel(), l\_heat(), l\_par()): Module containing the logicals that control the run
- radial\_functions(kappa(), r\_cmb(), dr\_fac(), rho0(), r\_icb(), topcond(), dtemp0(), temp0(), botcond(), d\_costf\_init(), r(), i\_costf\_init())
- blocking (sizethetab(), nthetabs(), lo\_map(), nfs()): Module containing blocking information
- useful (cc2real ()): library with several useful subroutines
- radial\_data(nrstop(), n\_r\_icb(), n\_r\_cmb(), nrstart())
- truncation (lm\_max(), n\_r\_max(), l\_max()): This module defines the grid points and the truncation
- integration(rint\_r(), rint()): Radial integration functions
- parallel\_mod: This module contains the blocking information
- output\_data(n\_misc\_file(), tag(), misc\_file()): This module contains the parameters for output control
- egeos mod (getegeos())
- constants (vol\_oc(), two(), pi(), one(), osq4pi(), sq4pi(), four()): module containing constants and parameters used in the code.
- num\_param(lscale()): Module containing numerical and control parameters
- lmloop\_data(ulm(), llm())

#### **Variables**

## **Subroutines and functions**

**subroutine** outmisc\_mod/**outmisc** (*timescaled*, *hellmr*, *hel2lmr*, *helnalmr*, *helna2lmr*, *nlogs*, *w*, *dw*, *ddw*, *z*, *dz*, *s*, *ds*, *geos*, *dpflow*, *dzflow*)

```
• timescaled [real,in]
```

- **hellmr** (*l* max+1,nrstop-(nrstart)+1) [real,in]
- hel2lmr (l\_max+1,nrstop-(nrstart)+1) [real,in]
- **helnalmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- helna2lmr (l\_max+1,nrstop-(nrstart)+1) [real,in]
- **nlogs** [integer,in]
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **ddw** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dz** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **s** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- ds (ulm-(llm)+1, $n\_r\_max$ ) [complex,in]
- **geos** [real,out]
- dpflow [real,out]
- **dzflow** [real,out]

```
Called from output ()
```

Call to lmas2pt(), rint(), getegeos()

## 10.15.6 outRot.f90

### **Quick access**

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (kbotv(), ktopv()): Module containing the physical parameters
- output\_data (n\_srma\_file(), n\_angular\_file(), n\_rot\_file(), srma\_file(), n\_sric\_file(), tag(), rot\_file(), sric\_file(), angular\_file()): This module contains the parameters for output control
- logic (l\_iner(), l\_mag(), l\_rot\_ic(), l\_srma(), l\_drift(), l\_rot\_ma(), l\_am(), l\_save\_out(), l\_sric(), l\_mag\_lf()): Module containing the logicals that control the run
- radial\_functions(drx(), r\_cmb(), r\_icb(), i\_costf\_init(), d\_costf\_init(), r())
- blocking (lm2(), st\_map(), lmstartb(), lo\_map(), lmstopb()): Module containing blocking information

- radial\_data(n\_r\_icb(), n\_r\_cmb())
- truncation (n\_phi\_max(), minc(), n\_r\_max(), n\_r\_maxmag(), nrp()): This module defines the grid points and the truncation
- integration(rint\_r(), rint()): Radial integration functions
- parallel\_mod: This module contains the blocking information
- grenoble (bic(), lgrenoble()): This module contains all variables for the case of an imposed IC dipole
- horizontal\_data (costheta(), gauss()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- constants (c\_moi\_ic(), third(), c\_moi\_oc(), y11\_norm(), two(), pi(), y10\_norm(), c\_moi\_ma(), half(), zero(), four()): module containing constants and parameters used in the code.
- num\_param(tscale(), 1scale(), vscale()): Module containing numerical and control parameters
- lmloop\_data(ulm(), llm(), llmmag(), ulmmag())

#### **Variables**

• outrot/get\_viscous\_torque [public]

#### **Subroutines and functions**

#### **Parameters**

- time [real,in]
- dt [real,in]
- ekinic [real,out]
- ekinma [real,out]
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- dz (ulm-(llm)+1,n\_r\_max) [complex,in]
- **b** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*,*in*]
- omega\_ic [real,in]
- omega\_ma [real,in]
- lorentz torque ic [real,in]
- lorentz\_torque\_ma [real,in]

Called from output ()

Call to sendvals\_to\_rank0(), get\_angular\_moment()

 $subroutine outrot/get\_viscous\_torque\_real (viscous\_torque, z10, dz10, r)$ 

Purpose of this subroutine is to calculate the viscous torque on mantle or inner core respectively. NOTE: sign is wrong for torque on mantle!

#### **Parameters**

- viscous torque [real,out]
- **z10** [real,in] :: z10 coefficient and its radial deriv.
- **dz10** [real,in]
- **r** [real,in] :: radius (ICB or CMB)

## **subroutine** outrot/**get\_viscous\_torque\_complex** (viscous\_torque, z10, dz10, r)

Purpose of this subroutine is to calculate the viscous torque on mantle or inner core respectively. NOTE: sign is wrong for torque on mantle!

#### **Parameters**

- viscous\_torque [real,out]
- z10 [complex,in] :: z10 coefficient and its radial deriv.
- **dz10** [complex,in]
- **r** [real,in] :: radius (ICB or CMB)

subroutine outrot/get\_lorentz\_torque (lorentz\_torque, nthetastart, sizethetab, br, bp, nr)

#### **Parameters**

- **lorentz\_torque** [real,inout] :: lorentz\_torque for theta(1:n\_theta)
- **nthetastart** [integer,in] :: first number of theta in block
- **sizethetab** [integer,in] :: size of theta bloching
- **br** (*nrp*,\*) [*real,in*] :: array containing
- **bp** (*nrp*,\*) [real,in] :: array containing
- **nr** [integer,in]

Called from do\_iteration\_thetablocking\_seq(), do\_iteration\_thetablocking\_openmp()

**subroutine** outrot/**get\_angular\_moment** (z10, z11, omega\_ic, omega\_ma, angular\_moment\_oc, angular\_moment\_ic, angular\_moment\_ma)

## **Parameters**

- **z10** (*n\_r\_max*) [complex,in]
- **z11** (*n\_r\_max*) [complex,in]
- omega\_ic [real,in]
- omega ma [real,in]
- angular\_moment\_oc (\*) [real,out]
- angular\_moment\_ic (\*) [real,out]
- angular\_moment\_ma (\*) [real,out]

Called from write\_rot(), updatez()

Call to rint\_r()

subroutine outrot/sendvals\_to\_rank0 (field, n\_r, lm\_vals, vals\_on\_rank0)

- **field**  $(ulm-(llm)+1,n\_r\_max)$  [complex,in]
- **n\_r** [integer,in]
- lm\_vals (\*) [integer,in]
- vals\_on\_rank0 (\*) [complex,out]

Called from write rot()

## 10.15.7 outPar.f90

#### Quick access

Variables fviscmeanr, gradt2meanr, smeanr, fcondmeanr, eparaximeanr, duhmeanr, uhmeanr, fconvmeanr, rolmeanru2, rmmeanr, dlvu2cmeanr, fkinmeanr, dlvmeanr, eparmeanr, rolmeanr, fresmeanr, eperpmeanr, dlvu2meanr, mvar, svar, eperpaximeanr, dlvcmeanr, fpoynmeanr

**Routines** initialize\_outpar\_mod(), outperppar(), outpar()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters(vischeatfac(), ohmlossfac(), ktops(), prmag(), kbots(), ek(), opr()): Module containing the physical parameters
- horizontal\_data(gauss()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_perppar(), l\_anel(), l\_mag\_nl(), l\_save\_out(), l\_viscbccalc(), l\_fluxprofs()): Module containing the logicals that control the run
- radial\_functions (i\_costf\_init(), sigma(), kappa(), dr\_fac(), r(), rho0(), d\_costf\_init(), or2(), temp0())
- blocking (sizethetab(), lm2m(), nthetabs(), nfs()): Module containing blocking information
- useful (cc2real ()): library with several useful subroutines
- fields (s\_rloc(), ds\_rloc()): This module contains the potential fields and their radial derivatives
- radial\_data(nrstop(), n\_r\_icb(), nrstopmag(), nrstartmag(), nrstart())
- truncation (l\_maxmag(), lm\_max(), n\_r\_max(), l\_max(), n\_r\_maxmag()): This module defines the grid points and the truncation
- integration (rint()): Radial integration functions
- parallel mod: This module contains the blocking information
- output\_data(n\_perppar\_file(), tag(), perppar\_file()): This module contains the parameters for output control
- constants (two(), pi(), osq4pi(), half(), sq4pi(), mass(), four()): module containing constants and parameters used in the code.
- num\_param(tscale()): Module containing numerical and control parameters
- legendre\_spec\_to\_grid(lmas2pt())

#### **Variables**

- outpar\_mod/dlvu2cmeanr (:) [real,private/allocatable]
- outpar\_mod/rolmeanru2 (:) [real,private/allocatable]
- outpar\_mod/rolmeanr(:) [real,private/allocatable]
- outpar\_mod/fcondmeanr (:) [real,private/allocatable]
- outpar\_mod/eperpaximeanr(:) [real,private/allocatable]
- outpar\_mod/dlvcmeanr (:) [real,private/allocatable]
- outpar\_mod/svar (:) [real,private/allocatable]
- outpar\_mod/mvar (:) [real, private/allocatable]
- outpar mod/**fkinmeanr**(:) [real,private/allocatable]
- outpar\_mod/fviscmeanr(:) [real,private/allocatable]
- outpar\_mod/eperpmeanr(:) [real,private/allocatable]
- outpar\_mod/eparmeanr (:) [real,private/allocatable]
- outpar\_mod/gradt2meanr(:) [real,private/allocatable]
- outpar\_mod/smeanr (:) [real,private/allocatable]
- outpar\_mod/fresmeanr (:) [real,private/allocatable]
- outpar\_mod/eparaximeanr (:) [real,private/allocatable]
- outpar\_mod/fpoynmeanr(:) [real,private/allocatable]
- outpar\_mod/dlvmeanr(:) [real,private/allocatable]
- outpar\_mod/uhmeanr(:) [real,private/allocatable]
- outpar\_mod/dlvu2meanr (:) [real,private/allocatable]
- outpar\_mod/duhmeanr(:) [real,private/allocatable]
- outpar\_mod/rmmeanr(:) [real,private/allocatable]
- outpar\_mod/fconvmeanr (:) [real,private/allocatable]

## Subroutines and functions

```
subroutine outpar_mod/initialize_outpar_mod()
```

## Called from magic

- timepassed [real,in]
- timenorm [real,in]
- **nlogs** [integer,in]
- l\_stop\_time [logical,in]

```
• ekinr (n_r_max) [real,in] :: kinetic energy w radius
                 • rolru2 (n_r_max) [real,in]
                • dlvr (n_r_max) [real,in]
                • dlvrc (n_r_max) [real,in]
                 • dlvru2 (n r max) [real,in]
                • dlvru2c (n r max) [real,in]
                • uhlmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                 • duhlmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                 • gradslmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • fconvlmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • fkinlmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • fvisclmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • fpoynlmr (l_maxmag+1,nrstopmag-(nrstartmag)+1) [real,in]
                 • freslmr (l_maxmag+1,nrstopmag-(nrstartmag)+1) [real,in]
                 • rmr (n_r_max) [real,out]
          Called from output ()
          Call to cc2real(), lmas2pt()
subroutine outpar_mod/outperppar (time, timepassed, timenorm, l_stop_time, eperplmr, eparlmr, eper-
                                         paxilmr, eparaxilmr)
          Parameters
                • time [real,in]
                 • timepassed [real,in]
                 • timenorm [real,in]
                • l_stop_time [logical,in]
                • eperplmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • eparlmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • eperpaxilmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                 • eparaxilmr (l_max+1,nrstop-(nrstart)+1) [real,in]
          Called from output()
          Call to lmas2pt(), rint()
10.15.8 power.f90
Quick access
     Variables curlu2meanr, buomeanr, ohmdissr
     Routines get_power(), initialize_output_power()
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (kbotv(), opm(), lffac(), ktopv()): Module containing the physical parameters
- horizontal\_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_mag(), l\_rot\_ic(), l\_srma(), l\_rot\_ma(), l\_conv(), l\_save\_out(), l\_cond\_ic(), l\_sric(), l\_heat()): Module containing the logicals that control the run
- radial\_functions (r\_ic(), drx(), d\_costf1\_ic\_init(), r\_cmb(), i\_costf1\_ic\_init(), i\_costf\_init(), r\_icb(), or2(), rgrav(), dr\_fac\_ic(), o\_r\_ic2(), o\_r\_ic(), d\_costf\_init(), r(), lambda())
- blocking (st\_map(), lmstartb(), lo\_map(), lmstopb()): Module containing blocking information
- useful (cc22real (), cc2real ()): library with several useful subroutines
- radial\_data(n\_r\_icb(), n\_r\_cmb())
- truncation (n\_r\_max(), n\_r\_maxmag(), n\_r\_ic\_maxmag(), n\_r\_ic\_max()): This module defines the grid points and the truncation
- integration(rint\_r(), rintic()): Radial integration functions
- parallel\_mod: This module contains the blocking information
- output\_data (power\_file(), tag(), n\_power\_file()): This module contains the parameters for output control
- outrot(get\_viscous\_torque())
- constants (one (), half (), two ()): module containing constants and parameters used in the code.
- num\_param (tscale(), escale()): Module containing numerical and control parameters
- lmloop\_data(ulm(), llm(), llmmag(), ulmmag())

#### **Variables**

- power/ohmdissr(:) [real,private/allocatable]
- power/buomeanr (:) [real,private/allocatable]
- power/curlu2meanr (:) [real,private/allocatable]

## **Subroutines and functions**

```
subroutine power/initialize_output_power()
```

```
Called from magic
```

This subroutine calculates power and dissipation of the core/mantle system. Energy input into the outer core is by buoyancy and possibly viscous accelarations at the boundaries if the rotation rates of inner core or mantle are prescribed and kept fixed. The losses are due to Ohmic and viscous dissipation. If inner core and mantel are allowed to change their rotation rates due to viscous forces this power is not lost from the system and has to be respected.

The output is written into a file power.TAG.

#### **Parameters**

```
• time [real,in]
```

- timepassed [real,in]
- timenorm [real,in]
- l\_stop\_time [logical,in]
- omega\_ic [real,in]
- omega\_ma [real,in]
- lorentz\_torque\_ic [real,in]
- lorentz\_torque\_ma [real,in]
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **ddw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- $\mathbf{z}$  (ulm-(llm)+1,n\_r\_max) [complex,in]
- dz (ulm-(llm)+1,n\_r\_max) [complex,in]
- $\mathbf{s}$  (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **b** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **ddb** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- aj (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **dj** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*,*in*]
- **db\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- **ddb ic** (ulmmag-(llmmag)+1,n r ic maxmag) [complex,in]
- $\bullet \ \ \mathbf{aj\_ic} \ (ulmmag-(llmmag)+1, n\_r\_ic\_maxmag) \ [complex, in] \\$
- **dj\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- viscdiss [real,out]
- **ohmdiss** [real,out]

```
Called from output ()
```

Call to cc2real(), cc22real(), rint\_r(), rintic()

## 10.15.9 spectra.f90

#### **Quick access**

```
Variables e_t_1 ave, e_t_m ave, e_cmb2_m ave, ek_p2_1 ave, ek_p2_m ave, ek_p2_1 ave, e_p2_1 ave, e_p2_2 ave, e_p2_1 ave, e_p2_2 ave,
```

```
ek_t2_1ave, dt_icb2_ave, t2_ave, e_cmb_1ave, ek_p_m_ave, e_t2_m_ave, ek_t_mave, t_icb_ave, dt_icb_ave, t_icb2_ave, e_cmb_mave, ek_t_1ave, e_p_1ave, e_t2_1ave
```

**Routines** get\_standard\_deviation(), spectrum(), spectrum\_temp\_average(), initialize\_spectra(), spectrum\_temp(), spectrum\_average()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (1ffac()): Module containing the physical parameters
- horizontal\_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_mag(), l\_anel(), l\_heat(), l\_cond\_ic()): Module containing the logicals that control the run
- radial\_functions (orho2(), drx(), d\_costfl\_ic\_init(), r\_ic(), i\_costfl\_ic\_init(), i\_costf\_init(), r\_icb(), or2(), orho1(), dr\_fac\_ic(), dr\_fac(), d\_costf\_init(), r())
- blocking (st\_map(), lo\_map()): Module containing blocking information
- useful (safeopen(), cc22real(), cc2real(), safeclose()): library with several useful subroutines
- radial\_data(n\_r\_icb(), n\_r\_cmb())
- truncation  $(n_r_{max}(), minc(), n_r_{ic_{max}mag}(), l_{max}(), n_r_{ic_{max}mag}(), n_r_{ic_{max}}())$ : This module defines the grid points and the truncation
- integration(rint\_r(), rintic(), rint()): Radial integration functions
- parallel\_mod: This module contains the blocking information
- output\_data (n\_u2\_spec\_file(), tag(), nlf(), n\_mag\_spec\_file(), log\_file(), n\_kin\_spec\_file()): This module contains the parameters for output control
- constants (one (), vol\_oc(), half(), four(), pi()): module containing constants and parameters used in the code.
- num\_param(tscale(), escale()): Module containing numerical and control parameters
- lmloop\_data(ulm(), llm(), llmmag(), ulmmag())

## **Variables**

- spectra/t\_ave(:) [real,private/allocatable]
- spectra/ek\_p\_l\_ave(:) [real,private/allocatable]
- spectra/e\_cmb2\_m\_ave (:) [real,private/allocatable]
- spectra/e\_p\_m\_ave(:) [real,private/allocatable]
- spectra/t\_icb\_ave (:) [real,private/allocatable]
- spectra/e\_t\_l\_ave(:) [real,private/allocatable]
- spectra/dt\_icb\_ave(:) [real,private/allocatable]

```
• spectra/ek_p_m_ave(:) [real,private/allocatable]
   • spectra/ek_t_m_ave(:) [real,private/allocatable]
   • spectra/e_p2_m_ave(:) [real,private/allocatable]
   • spectra/ek_t2_1_ave (:) [real,private/allocatable]
   • spectra/ek_p2_1_ave (:) [real,private/allocatable]
   • spectra/e_p2_1_ave (:) [real,private/allocatable]
   • spectra/e_cmb_l_ave(:) [real,private/allocatable]
   • spectra/ek_t2_m_ave(:) [real,private/allocatable]
   • spectra/e_cmb_m_ave(:) [real,private/allocatable]
   • spectra/e_t_m_ave (:) [real,private/allocatable]
   • spectra/dt_icb2_ave(:) [real,private/allocatable]
   • spectra/e_p_l_ave (:) [real,private/allocatable]
   • spectra/e_cmb2_1_ave (:) [real,private/allocatable]
   • spectra/ek_t_l_ave(:) [real,private/allocatable]
   • spectra/t2_ave(:) [real,private/allocatable]
   • spectra/e t2 m ave(:) [real,private/allocatable]
   • spectra/ek_p2_m_ave(:) [real,private/allocatable]
   • spectra/e_t2_1_ave (:) [real,private/allocatable]
   • spectra/t_icb2_ave(:) [real,private/allocatable]
Subroutines and functions
subroutine spectra/initialize_spectra()
          Called from magic
subroutine spectra/spectrum average (n time ave, l stop time, time passed, time norm, b, ai, db,
          Parameters
                • n_time_ave [integer,in]
               • l_stop_time [logical,in]
               • time_passed [real,in]
                • time_norm [real,in]
                • b (ulm-(llm)+1,n_r_max) [complex,in]
               • aj (ulm-(llm)+1,n\_r\_max) [complex,in]
                • db (ulm-(llm)+1,n_r_max) [complex,in]
               • bv [character,in]
          Called from output ()
          Call to cc2real(), rint r(), get standard deviation(), safeopen(),
```

safeclose()

**function** spectra/**get\_standard\_deviation** (dt\_norm, mean, sum\_of\_squares)

#### **Parameters**

- dt\_norm [real,in]
- mean [real,in]
- sum of squares [real,in]

**Return stdev** [real]

Called from spectrum\_temp\_average(), spectrum\_average()

**subroutine** spectra/**spectrum** (*time*, *n\_spec*, *w*, *dw*, *z*, *b*, *db*, *aj*, *b\_ic*, *db\_ic*, *aj\_ic*)

calculates magnetic energy = 1/2 Integral(B<sup>2</sup> dV) integration in theta,phi by summation over harmonic coeffs. integration in r by Chebycheff integrals

Output: enbp: Total poloidal enbt: Total toroidal apome: Axisym. poloidal atome: Axisym. toroidal

## **Parameters**

- time [real,in]
- **n\_spec** [integer,in] :: number of spectrum/call, file
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dw** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **b** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **db** (*ulmmag-(llmmag*)+1,*n\_r\_maxmag*) [*complex*,*in*]
- **aj** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **b\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- **db\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- aj\_ic (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]

Called from output(), fields\_average()

Call to cc2real(), rint\_r(), cc22real(), rintic()

## **Parameters**

- n\_time\_ave [integer,in]
- l\_stop\_time [logical,in]
- time\_passed [real,in]
- time\_norm [real,in]
- $s(ulm-(llm)+1,n_r_max)[complex,in]$
- ds (ulm-(llm)+1, $n_r_max$ ) [complex,in]

Called from output()

Call to cc2real(), rint(), get\_standard\_deviation(), safeopen(),
 safeclose()

```
subroutine spectra/spectrum_temp (time, n_spec, s, ds)
```

calculates spectra of temperature and composition

#### **Parameters**

- time [real,in]
- **n\_spec** [integer,in] :: number of spectrum/call, file
- **s** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **ds** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]

```
Called from output(), fields_average()
```

Call to cc2real(), rint()

# 10.16 IO: graphic files, movie files, coeff files and potential files

## 10.16.1 out\_graph\_file.f90

#### **Quick access**

```
Routines graphout(), graphout_ic(), graphout_mpi_header(), graphout_mpi(), graph write mpi(), graph write()
```

### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (radratio(), sigma\_ratio(), prmag(), ra(), pr(), ek()): Module containing the physical parameters
- horizontal\_data (dlh(), plm(), theta\_ord(), dplm(), o\_sin\_theta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_mag(), l\_cond\_ic()): Module containing the logicals that control the run
- radial\_functions (r\_ic(), o\_r\_ic2(), r\_cmb(), or1(), r\_icb(), or2(), r(), orho1(), o\_r\_ic())
- blocking (sizethetab(), nthetabs(), nfs()): Module containing blocking information
- fft\_jw: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- radial\_data(n\_r\_icb())
- truncation (n\_r\_max(), n\_theta\_max(), lm\_max(), nrp(), n\_phi\_tot(), n\_phi\_max(), lm\_maxmag(), minc(), l\_max(), n\_r\_maxmag(), n\_r\_ic\_max(), n\_r\_ic\_maxmag()): This module defines the grid points and the truncation
- parallel\_mod: This module contains the blocking information
- output\_data(graph\_mpi\_fh(), n\_graph\_file(), runid()): This module contains the parameters for output control
- num\_param (vscale()): Module containing numerical and control parameters
- legendre\_spec\_to\_grid(legtf())

• leg\_helper\_mod(legprep\_ic())

# **Variables**

# **Subroutines and functions**

```
subroutine graphout_mod/graphout (time, n_r, vr, vt, vp, br, bt, bp, sr, n_theta_start, n_theta_block_size, lgraphheader)
```

Output of components of velocity, magnetic field vector and entropy for graphics.

- •n\_r: (input) for  $n_r = 0$  a header is written. for  $n_r > 0$  values at radial level  $n_r$  are written
- •vr...sr: (input) arrays with grid-point values
- •n\_theta\_start : (input) values are written for theta-points : n\_theta\_start <= n\_theta
  <= n\_theta\_start-1+n\_theta\_block</pre>

# **Parameters**

- time [real,in]
- **n\_r** [integer,in] :: radial grod point no.
- **vr** (*nrp*,\*) [real,in]
- **vt** (*nrp*,\*) [real,in]
- **vp** (*nrp*,\*) [real,in]
- **br** (*nrp*,\*) [*real*,*in*]
- **bt** (*nrp*,\*) [*real*,*in*]
- **bp** (*nrp*,\*) [real,in]
- **sr** (*nrp*,\*) [*real*,*in*]
- n\_theta\_start [integer,in] :: start theta no.
- n\_theta\_block\_size [integer,in] :: size of theta block
- **lgraphheader** [logical,inout]

```
Called from fields_average()
```

Call to graph\_write()

**subroutine** graphout\_mod/**graphout\_mpi** (time,  $n_-r$ , vr, vt, vp, br, bt, bp, sr,  $n_-theta_\_start$ ,  $n_-theta_\_block_\_size$ , lgraphheader)

MPI version of the graphOut subroutine (use of MPI\_IO)

- time [real,in]
- **n\_r** [integer,in] :: radial grod point no.
- **vr** (*nrp*,\*) [real,in]
- **vt** (*nrp*,\*) [real,in]
- **vp** (*nrp*,\*) [real,in]
- **br** (*nrp*,\*) [*real*,*in*]

- **bt** (*nrp*,\*) [real,in]
- **bp** (*nrp*,\*) [real,in]
- **sr** (*nrp*,\*) [real,in]
- n\_theta\_start [integer,in] :: start theta no.
- n theta block size [integer,in] :: size of theta block
- **lgraphheader** [logical,inout]

**Called from** do\_iteration\_thetablocking\_seq(), do\_iteration\_thetablocking\_openmp()

```
Call to graph_write_mpi()
```

**subroutine** graphout\_mod/**graphout\_mpi\_header** (time, n\_r, n\_theta\_start, n\_theta\_block\_size)

Writes the header (MPI version)

# **Parameters**

- time [real,in]
- **n\_r** [integer,in] :: radial grod point no.
- n\_theta\_start [integer,in] :: start theta no.
- n\_theta\_block\_size [integer,in] :: size of theta block

Called from radialloopg()

```
subroutine graphout_mod/graphout_ic (b_ic, db_ic, ddb_ic, aj_ic, dj_ic, b)
```

Purpose of this subroutine is to write inner core magnetic field onto graphic output file. If the inner core is insulating (l\_cond\_ic=false) the potential field is calculated from the outer core field at r=r\_cmb. This version assumes that the fields are fully local on the rank which is calling this routine (usually rank 0).

# **Parameters**

- **b\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **db\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- ddb\_ic (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **aj\_ic** (*lm\_maxmag*,*n\_r\_ic\_maxmag*) [*complex*,*in*]
- **dj ic** (lm maxmag,n r ic maxmag) [complex,in]
- **b** (lm\_maxmag,n\_r\_maxmag) [complex,in]

Called from output(), fields\_average()

```
Call to legprep_ic(), legtf(), fft_thetab(), graph_write_mpi()
```

**subroutine** graphout\_mod/**graph\_write** (*n\_phis*, *n\_thetas*, *dummy*, *n\_graph\_file*)

This subroutine writes the data for one theta-band (stored in 'dummy'). Version May, 5, 2000.

- **n\_phis** [integer,in] :: number of logitudes to be printed
- **n thetas** [integer, in] :: number of first colatitude value

- **dummy** (n\_phi\_max,\*) [real,in] :: data
- **n\_graph\_file** [integer,in] :: output unit

Called from graphout ()

**subroutine** graphout\_mod/**graph\_write\_mpi**(n\_phis, n\_thetas, dummy, graph\_mpi\_fh)

#### **Parameters**

- **n phis** [integer,in]:: number of logitudes to be printed
- n\_thetas [integer,in] :: number of first colatitude value
- **dummy** (n\_phi\_max,\*) [real,in] :: data
- graph\_mpi\_fh [integer,in] :: mpi handle of the mpi file

Called from graphout\_ic(), graphout\_mpi()

# 10.16.2 movie.f90

#### **Quick access**

Variables n\_movie\_fields\_max, n\_movies\_max, movie, movie\_file, frames, movie\_const, t\_movies, lstoremov, n\_movie\_fields, n\_movie\_field\_start, n\_movie\_const, licfield, n\_movie\_field\_stop, n\_movie\_file, n\_movie\_field\_type, n\_movie\_fields\_ic, n\_movie\_surface, n\_movie\_type, moviedipcolat, moviedipstrength, moviediplon, moviedipstrengthgeo, n movies, n frame work, n md

**Routines** initialize\_movie\_data(), get\_movie\_type(), finalize\_movie\_data(), movie\_gather\_frames\_to\_rank0()

- precision\_mod: This module controls the precision used in MagIC
- horizontal\_data(theta(), phi()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_dtbmovie(), l\_htmovie(), l\_movie\_oc(), l\_store\_frame(), l\_movie(), l\_save\_out(), l\_movie\_ic()): Module containing the logicals that control the run
- output\_data(n\_log\_file(), tag(), log\_file()): This module contains the parameters for output control
- radial\_functions(r\_ic(), r(), r\_cmb(), r\_icb())
- useful (logwrite()): library with several useful subroutines
- constants (one (), pi ()): module containing constants and parameters used in the code.
- radial\_data(nrstop(), n\_r\_icb(), n\_r\_cmb(), nrstart())
- charmanip (length\_to\_blank(), delete\_string(), capitalize(), str2dble()): This module contains several useful routines to manipule character strings
- truncation (n\_phi\_max(), ldtbmem(), n\_r\_max(), minc(), n\_theta\_max(), n\_r\_tot(), lmoviemem(), n\_r\_ic\_max()): This module defines the grid points and the truncation

• parallel\_mod: This module contains the blocking information

# **Variables**

- movie\_data/lstoremov(30)[logical,public]
- movie\_data/t\_movies(10000)[real,public]
- movie\_data/licfield(30)[logical,public]
- movie\_data/movie\_file (30) [character,public]
- movie\_data/movie (30) [character,public]
  Only for input
- movie\_data/n\_frame\_work [integer,public]
- movie\_data/n\_movie\_fields\_max [integer,parameter=6/public]
   Max no. of fields per movie
- movie data/n movie fields (30) [integer, public]
- movie\_data/n\_movie\_surface (30) [integer,public]
- movie\_data/n\_movie\_type (30) [integer, public]
- movie\_data/moviedipstrengthgeo [real,public]
- movie\_data/n\_movie\_field\_type (6,30) [integer,public]
- movie\_data/frames (:) [real,allocatable/public]
- movie\_data/n\_movie\_file (30) [integer,public]
- movie\_data/moviediplon [real,public]
- movie\_data/moviedipcolat [real,public]
- movie\_data/moviedipstrength [real,public]
- movie\_data/n\_movies [integer,public]
- movie\_data/n\_movie\_const (30) [integer,public]
- movie\_data/n\_movie\_fields\_ic (30) [integer, public]
- movie\_data/n\_movie\_field\_stop (6,30) [integer, public]
- movie\_data/movie\_const (30) [real,public]
- movie\_data/n\_movie\_field\_start (6,30) [integer,public]
- movie\_data/n\_movies\_max [integer,parameter=30/public]
   Max no. of different movies
- movie\_data/n\_md [integer, public]

# **Subroutines and functions**

#### subroutine movie data/initialize movie data()

This routine is called during the initialization of the code. It allows to:

- •Estimate the required memory imprint and allocate the arrays accordingly
- •Open the requested movie files

# Called from magic

Call to get\_movie\_type(), logwrite()

# subroutine movie\_data/finalize\_movie\_data()

Close movie files

Called from magic

# subroutine movie data/get movie type()

Purpose of this subroutine is to identify the different movie types from the input string movies(\*). Note that generally blanks are not interpreted and that the interpretation is not case sensitive. In general two informations are needed:

- 1.A word FIELDINFO that identifies the field to be plotted (e.g. Br for radial magnetic field, see list below) Possible keywords are (optional text in brackets):
  - •B r[adial] : radial magnetic field
  - •B t[heta]: theta component
  - •B p[hi]: azimuthal component
  - •B h[orizontal] : the two horizontal components
  - •B a[ll]: all three components
  - •FIELDLINE[S]: field lines of axisymmetric or FL poloidal field for phi=constant
  - •AX[ISYMMETRIC] B or AB: axisymmetric phi component of the magnetic field for phi=constant
  - •V r[adial]: radial velocity field
  - •V t[heta]: theta component
  - •V p[hi]: azimuthal component
  - •V h[orizontal] : the two horizontal components
  - •V a[ll]: all three components
  - •STREAMLINE[S]: field lines of axisymmetric or SL: poloidal field for phi=constant
  - •AX[ISYMMETRIC] V or AV : axisymmetric phi component of the velocity field for phi=constant
  - •V z : z component of velocity at equator and z component of the vorticity at the equator (closest point to equator)
  - •Vo z : z-component of vorticity
  - •Vo r : r-component of vorticity
  - •Vo p : phi-component of vorticity
  - •T[emperature] : sic
  - •AX[ISYMMETRIC] T or AT: axisymmetric T field for phi=constant
  - •Heat t[ransport]: radial derivative of T
  - •FL Pro: axisymmetric field line stretching
  - •FL Adv: axisymmetric field line advection
  - •FL Dif: axisymmetric field line diffusion
  - •AB Pro: axisymmetric (tor.) Bphi production
  - •AB Dif: axisymmetric (tor.) Bphi diffusion

```
Br Pro: Br productionBr Adv: Br advectionBr Dif: Br diffusionJr: Jr production
```

•Jr Pro : Jr production + omega effects

Jr Adv : Jr advectionJr Dif : Jr diffusionBz Pol : poloidal Bz

Bz Pol Pro: poloidal Bz production
Bz Pol Adv: poloidal Bz advection
Bz Pol Dif: poloidal Bz diffusion

•Jz Tor: poloidal Jz

Jz Tor Pro: poloidal Jz productionJz Tor Adv: poloidal Jz advectionJz Tor Dif: poloidal Jz diffusion

•Bp Tor: toriodal Bphi

Bp Tor Pro: toriodal Bphi production
Bp Tor Adv: toriodal Bphi advection
Bp Tor Dif: toriodal Bphi diffusion

•HEL[ICITY] : sic

•AX[ISYMMETRIC HELICITY] or AHEL: axisymmetric helicity

•Bt Tor : toroidal Btheta •Pot Tor : toroidal Potential

Pol Fieldlines : toroidal PotentialBr Shear : azimuthal Shear of Br

•Lorentz[force] : Lorentz force (only phi component)

•Br Inv: Inverse field apperance at CMB

2.A second information that identifies the coordinate to be kept constant (surface). E.g. r=number for surface r=constant with number given in units of the total core radius or theta/phi=number with number given in degrees Four keywords are also possible:

•CMB : core mantle boundary
•EQ[UATOR] : equatorial plane
•SUR[FACE] : Earth surface (only magnetic field)
•3[D] : 3D field throughout the OC [and IC for B]

On output the necessary information is coded into integers and is used in this form by further subroutines:

•n\_movies = total number of movies

•n\_type(n\_movie) = movie type:

- -= 1 : Radial magnetic field
- -= 2 : Theta component of magnetic field
- -= 3 : Azimuthal magnetic field
- -= 4: Horizontal magnetic field
- -= 5 : Total magnetic field (all compnents)
- -= 8 : Axisymmetric azimuthal magnetic field (phi=constant)
- -= 9 : 3d magnetic field
- -= 11: Radial velocity field
- -= 12: Theta component of velocity field
- -= 13 : Azimuthal velocity field
- -= 14: Horizontal velocity field
- -= 15 : Total velocity field (all compnents)
- -= 17 : Scalar field whose contours are the stream lines of the axisymm. poloidal velocity field (phi=constant)
- -= 18 : Axisymmetric azimuthal velocity field (phi=constant)
- -= 19: 3d velocity field
- -= 20 : z component of vorticity
- -= 21 : Temperature field
- -= 22 : radial conv. heat transport
- **-=** 23 : helicity
- -= 24 : axisymmetric helicity
- -= 25 : phi component of vorticity
- -= 26 : radial component of vorticity
- -= 28 : axisymmetric Temperature field for phi=const.
- -= 29 : 3d temperature field
- -= 30 : Scalar field whose contours are the fieldlines of the axisymm. poloidal magnetic field (phi=constant)
- -= 31 : field line production
- -= 32 : field line advection
- -= 33 : field line diffusion
- -= 40 : Axisymmetric azimuthal magnetic field (phi=constant)
- -= 41 : Axis. Bphi production + omega eff.
- -= 42 : Axis. Bphi advection
- -= 43 : Axis. Bphi diffusion
- -= 44 : Axis. Bphi str.,dyn.,omega,diff.
- -= 50 : Bz
- **−=** 51 : Bz production

- -= 52 : Bz advection
- -= 53 : Bz diffusion
- -= 60 : toroidal Bphi
- -= 61 : toroidal Bphi production + omega eff.
- -= 62 : toroidal Bphi advection
- -= 63: toroidal Bphi diffusion
- -= 71 : Br production
- -= 72 : Br advection
- -=73: Br diffusion
- -= 80 : Jr
- -= 81 : Jr production
- -= 82 : Jr advection
- -= 83 : Jr diffusion
- -= 90 : poloidal Jz pol.
- -= 91 : poloidal Jz pol. production
- -= 92 : poloidal Jz advection
- -= 93 : poloidal Jz diffusion
- -= 94 : z component of velovity
- -= 95 : toroidal Btheta
- -= 96 : toroidal Potential
- -= 97 : Function for Poloidal Fieldlines
- -= 98 : azimuthal shear of Br
- -= 99 : phi component of Lorentz force
- -=101 : Stress fields
- -=102 : Force fields
- -=103: Br Inverse appearence at CMB
- -=110: radial heat flow
- -=111: Vz and Vorz north/south correlation
- -=112 : axisymm dtB tersm for Br and Bp
- -=113: axisymm dSdr
- -=114: Cylindrically radial magnetic field
- •n\_movie\_surface(n\_movie) = defines surface
- •n\_movie\_surface = 1 : r=constant:
  - -2: theta=constant
  - -3: phi=constant
  - --1: r=constant, Earth surface

- **-**0 : 3d volume
- •n\_movie\_fields(n\_movie) = no. of fields for outer core
- •n\_movie\_fields\_ic(n\_movie) = no. of fields for inner core
- •n\_movie\_field\_type(n\_field,n\_movie) = defines field
- •n\_movie\_field\_type:
  - -= 1 : radial magnetic field
  - -= 2 : theta comp. of the magnetic field
  - -= 3 : azimuthal magnetic field
  - -= 4 : radial velocity field
  - -= 5 : theta comp. of the velocity field
  - -= 6: azimuthal velocity field
  - -= 7: temperature field
  - -= 8 : scalar field for field lines
  - -= 9 : axisymm. toroidal mag. field
  - -=10: scalar field for stream lines
  - -=11: axisymm. v\_phi
  - **-=**12 : axisymm. T
  - -=13 : z-comp. of poloidal Bz
  - -=14 : z-comp. of poloidal Jz
  - -=15 : z-comp. of velocity
  - **-=**16 : z-comp. of vorticity
  - −=17 : radial derivative of T \* vr
  - -=18: helicity
  - -=19: axisymmetric helicity
  - -=20: axisymm field-line production
  - -=21: axisymm field-line advection
  - -=22 : axisymm field-line diffusion
  - -=23: axisymm Bphi production
  - -=24 : axisymm Bphi omega effect
  - -=25: axisymm Bphi advection
  - -=26: axisymm Bphi diffusion
  - -=27: Br production
  - -=28: Br advection
  - -=29: Br diffusion
  - **-=**30 : Jr
  - -=31: Jr production

- -=32: Jr omega effect
- -=33: Jr advection
- -=34 : Jr diffusion
- -=35 : poloidal Bz production
- -=36: poloidal Bz advection
- -=37 : poloidal Bz diffusion
- -=38 : poloidal Jz production
- -=39 : poloidal Jz omega effect
- -=40: poloidal Jz advection
- -=41 : poloidal Jz diffusion
- -=42: toroidal Bp
- -=43: toroidal Bp production
- -=44: toroidal Bp omega effect
- -=45: toroidal Bp advection
- -=46: toroidal Bp diffusion
- **-=**47 : phi-comp. of vorticity
- -=48 : r-comp. of vorticity
- -=49: toroidal Bp omega effect
- -=50: toroidal Bt
- -=51: toroidal Potential
- -=52 : poloidal Fieldlines in theta=const
- -=53: Br dr ( vp/(r sin(theta))
- -=54 : phi Lorentz force
- -=61 : AS phi reynolds stress force
- -=62 : AS phi advective stress force
- -=63 : AS phi viscous stress force
- -=64 : AS phi Lorentz force
- -=66: time derivative of axisym. v phi
- -=67: relative strength of axisym. v phi
- -=81: Br inverse appearence at CMB
- -=91 : radial derivative of T
- -=92 : Vz north/south correlation
- -=93: Vorz north/south correlation
- -=94: Hel north/south correlation
- -=101: AS poloidal Br production
- -=102: AS poloidal Br dynamo term

```
-=103: AS poloidal Br diffusion
```

-=104: AS toroidal Bp production

-=105: AS toroidal Bp dynamo term

-=106: AS toroidal Bp omega effect

-=107: AS toroidal Bp diffusion

-=108: Bs

•n\_movie\_field\_start(n\_field,n\_movie) = defines where first element of a field is stored in frames (\*)

•n\_movie\_field\_stop(n\_field,n\_movie) = defines where last element of a field is stored in frames (\*)

•The subroutine also defines appropriate file names for the movie files. These generally have the form TYPE\_mov.TAG

```
Called from initialize_movie_data()
Call to delete_string(), capitalize(), length_to_blank(), str2dble()
```

subroutine movie\_data/movie\_gather\_frames\_to\_rank0()

MPI communicators for movie files

Called from output ()

# 10.16.3 out movie file.f90

#### **Quick access**

```
Routines store\_fields\_r(), get\_sl(), get\_b\_surface(), store\_movie\_frame(), store\_fields\_t(), store\_fields\_3d(), store\_fields\_p(), store\_fields\_sur(), get\_fl(), write\_movie\_frame()
```

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (radratio(), pr(), ra(), prmag(), ek(), lffac()): Module containing the physical parameters
- horizontal\_data(costheta(), osn1(), dlh(), dphi(), theta\_ord(), d\_1(), sintheta(), plm(), o\_sin\_theta\_e2(), dplm(), o\_sin\_theta(), phi(), n\_theta\_cal2ord()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_save\_out(), l\_cond\_ic()): Module containing the logicals that control the run
- radial\_functions (orho2(), or4(), beta(), or1(), r\_ic(), r\_surface(), or3(), or2(), r(), orho1(), r\_cmb())
- blocking (1m2(), nfs(), 1m21()): Module containing blocking information
- fft\_jw (fft\_thetab()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- fields (b\_ic(), b(), b\_rloc(), w\_rloc()): This module contains the potential fields and their radial derivatives
- radial\_data(n\_r\_icb())

- movie\_data (lstoremov(), n\_movie\_file(), moviediplon(), moviedipcolat(),
   moviedipstrength(), n\_movies(), movie\_file(), n\_movie\_fields\_ic(), t\_movies(),
   n\_movie\_fields(), n\_movie\_field\_stop(), n\_movie\_surface(), n\_movie\_type(),
   n\_movie\_field\_start(), moviedipstrengthgeo(), n\_movie\_field\_type(),
   n\_movie\_const(), movie\_const(), frames())
- truncation (n\_r\_max(), n\_theta\_max(), lm\_maxmag(), n\_r\_ic\_maxmag(), n\_m\_max(), nrp(), n\_phi\_max(), lm\_max(), minc(), l\_max(), n\_r\_maxmag(), n\_r\_ic\_max()): This module defines the grid points and the truncation
- output\_data(runid()): This module contains the parameters for output control
- out\_dtb\_frame(write\_dtb\_frame())
- constants (one (), zero (), two ()): module containing constants and parameters used in the code.
- num\_param(tscale(), vscale()): Module containing numerical and control parameters

# **Variables**

# **Subroutines and functions**

**subroutine** out\_movie/**store\_movie\_frame** (*n\_r*, *vr*, *vt*, *vp*, *br*, *bt*, *bp*, *sr*, *drsr*, *dvrdp*, *dvpdr*, *dvtdr*, *dvrdt*, *cvr*, *cbr*, *cbt*, *n\_theta\_start*, *n\_theta\_block*, *bcmb*)

Controls output of movie frames. Usually called from radialLoop.

- **n\_r** [integer,in] :: radial grid point no.
- **vr** (*nrp*,\*) [real,in]
- **vt** (*nrp*,\*) [real,in]
- **vp** (*nrp*,\*) [real,in]
- **br** (*nrp*,\*) [*real*,*in*]
- **bt** (*nrp*,\*) [*real*,*in*]
- **bp** (*nrp*,\*) [*real*,*in*]
- **sr** (*nrp*,\*) [real,in]
- **drsr** (*nrp*,\*) [*real*,*in*]
- **dvrdp** (*nrp*,\*) [*real*,*in*]
- **dvpdr** (*nrp*,\*) [*real*,*in*]
- **dvtdr** (*nrp*,\*) [real,in]
- **dvrdt** (*nrp*,\*) [real,in]
- **cvr** (*nrp*,\*) [real,in]
- **cbr** (*nrp*,\*) [*real*,*in*]
- **cbt** (*nrp*,\*) [real,in]
- n\_theta\_start [integer,in] :: start theta no.
- n theta block [integer,in] :: size of theta block

• **bcmb** (*lm\_max*) [*complex*,*in*]

Writes different movie frames into respective output files. Called from rank 0 with full arrays in standard LM order.

# **Parameters**

- n\_frame [integer,in]
- time [real,in]
- **b** (lm\_maxmag,n\_r\_maxmag) [complex,in]
- **db** (lm\_maxmag,n\_r\_maxmag) [complex,in]
- **aj** (lm\_maxmag,n\_r\_maxmag) [complex,in]
- **dj** (lm\_maxmag,n\_r\_maxmag) [complex,in]
- **b\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **db\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- aj\_ic (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **dj\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- omega\_ic [real,in]
- omega\_ma [real,in]

```
Called from output ()
```

Call to write\_dtb\_frame()

Purpose of this subroutine is to store movie frames for surfaces r=const. into array frame(,)

# **Parameters**

- n store last [integer,in] :: Start position for storing -1
- **n\_field\_type** [integer,in] :: Defines field type
- n\_theta\_start [integer,in] :: Beginning of theta block
- n\_theta\_block [integer,in] :: Size of theta block
- **bcmb** (*lm\_max*) [*complex*, *in*]

Called from store\_movie\_frame()

Call to get\_b\_surface()

**subroutine** out\_movie/**store\_fields\_r** (*vr*, *vt*, *vp*, *br*, *bt*, *bp*, *sr*, *drsr*, *dvrdp*, *dvpdr*, *dvtdr*, *dvrdt*, *cvr*,  $n_r$ ,  $n_s$ tore\_last,  $n_s$ tield\_type,  $n_s$ theta\_start,  $n_s$ theta\_block)

Purpose of this subroutine is to store movie frames for surfaces r=const. into array frame(,)

#### **Parameters**

```
• vr (nrp,*) [real,in]
```

- **vt** (*nrp*,\*) [real,in]
- **vp** (*nrp*,\*) [real,in]
- **br** (*nrp*,\*) [*real*,*in*]
- **bt** (*nrp*,\*) [real,in]
- **bp** (*nrp*,\*) [real,in]
- **sr** (*nrp*,\*) [*real*,*in*]
- **drsr** (*nrp*,\*) [*real*,*in*]
- **dvrdp** (*nrp*,\*) [*real,in*]
- **dvpdr** (nrp,\*) [real,in]
- **dvtdr** (*nrp*,\*) [real,in]
- **dvrdt** (nrp,\*) [real,in]
- **cvr** (*nrp*,\*) [real,in]
- **n\_r** [integer,in]
- **n\_store\_last** [integer,in] :: Start position in frame(\*)-1
- **n\_field\_type** [integer,in] :: Defines field type
- n\_theta\_start [integer,in] :: Beginning of theta block
- n\_theta\_block [integer,in] :: Size of theta block

Called from store\_movie\_frame()

Purpose of this subroutine is to store movie frames for surfaces phi=const. into array frames(,)

- **vr** (*nrp*,\*) [real,in]
- **vt** (*nrp*,\*) [real,in]
- **vp** (*nrp*,\*) [real,in]
- **br** (*nrp*,\*) [*real*,*in*]
- **bp** (*nrp*,\*) [real,in]
- **bt** (*nrp*,\*) [*real*,*in*]
- **sr** (*nrp*,\*) [real,in]
- **drsr** (*nrp*,\*) [*real*,*in*]
- **dvrdp** (*nrp*,\*) [*real,in*]
- **dvpdr** (*nrp*,\*) [*real*,*in*]

```
dvtdr (nrp,*) [real,in]
dvrdt (nrp,*) [real,in]
cvr (nrp,*) [real,in]
cbr (nrp,*) [real,in]
cbt (nrp,*) [real,in]
n_r [integer,in] :: No. of radial point
n_store_last [integer,in] :: Start position in frame(*)-1
n_field_type [integer,in] :: Defines field type
n_phi_const [integer,in] :: No. of surface phi
n_field_size [integer,in] :: Size of field
n_theta_start [integer,in] :: Beginning of theta block
n_theta_block [integer,in] :: Size of theta block
```

**subroutine** out\_movie/**store\_fields\_t** (*vr*, *vt*, *vp*, *br*, *bt*, *bp*, *sr*, *drsr*, *dvrdp*, *dvpdr*, *dvtdr*, *dvrdt*, *cvr*, *cbt*, *n\_r*, *n\_store\_last*, *n\_field\_type*, *n\_theta\_const*, *n\_theta*)

Purpose of this subroutine is to store movie frames for surfaces r=const. into array frame(,)

#### **Parameters**

• **vr** (*nrp*,\*) [real,in]

**Call to** *get\_fl()*, *get\_sl()* 

Called from store\_movie\_frame()

- **vt** (*nrp*,\*) [real,in]
- **vp** (*nrp*,\*) [real,in]
- **br** (*nrp*,\*) [real,in]
- **bt** (*nrp*,\*) [real,in]
- **bp** (*nrp*,\*) [real,in]
- **sr** (*nrp*,\*) [*real*,*in*]
- **drsr** (*nrp*,\*) [*real,in*]
- dvrdp (nrp,\*) [real,in]
- **dvpdr** (*nrp*,\*) [real,in]
- **dvtdr** (*nrp*,\*) [*real,in*]
- **dvrdt** (*nrp*,\*) [*real*,*in*]
- **cvr** (*nrp*,\*) [real,in]
- **cbt** (*nrp*,\*) [*real*,*in*]
- **n\_r** [integer,in] :: No. of radial grid point
- **n\_store\_last** [integer,in] :: Position in frame(\*)-1
- n\_field\_type [integer,in] :: Defines field
- n\_theta\_const [integer,in] :: No. of theta to be stored

• **n\_theta** [integer,in] :: No. of theta in block

```
Called from store_movie_frame()
```

Purpose of this subroutine is to store movie frames for surfaces r=const. into array frame(,)

# **Parameters**

- **vr** (*nrp*,\*) [real,in]
- **vt** (*nrp*,\*) [real,in]
- **vp** (*nrp*,\*) [real,in]
- **br** (*nrp*,\*) [*real*,*in*]
- **bt** (*nrp*,\*) [real,in]
- **bp** (*nrp*,\*) [*real*,*in*]
- **sr** (*nrp*,\*) [*real*,*in*]
- **drsr** (*nrp*,\*) [*real*,*in*]
- **dvrdp** (*nrp*,\*) [*real*,*in*]
- **dvpdr** (*nrp*,\*) [*real,in*]
- **dvtdr** (*nrp*,\*) [*real*,*in*]
- **dvrdt** (*nrp*,\*) [real,in]
- **cvr** (*nrp*,\*) [real,in]
- **cbr** (*nrp*,\*) [*real*,*in*]
- **cbt** (*nrp*,\*) [real,in]
- n\_r [integer,in] :: No. of radial grid point
- **n\_store\_last** [integer,in] :: Position in frame(\*)-1
- n\_field\_type [integer,in] :: Defines field
- n\_theta\_start [integer,in] :: No. of first theta to block
- n\_theta\_block [integer,in] :: Size of theta block

Called from store\_movie\_frame()

```
subroutine out_movie/get_sl (sl, n_r, n_theta_start, n_theta_block)
```

Return field sl whose contourlines are the stream lines of the axisymmetric poloidal velocity field.  $sl(r,theta)=d_theta v(r,theta,m=0)/r$ 

- sl (\*) [real,out] :: Field for field lines
- **n\_r** [integer,in] :: No. of radial grid point
- n\_theta\_start [integer,in] :: No. of theta to start with
- n\_theta\_block [integer,in] :: Size of theta block

```
Called from store_fields_p()
```

```
subroutine out_movie/get_fl (fl, n_r, n_theta_start, n_theta_block, l_ic)
```

Return field fl whose contourlines are the fields lines of the axisymmetric poloidal mangetic field.

```
fl(r,theta)=d_theta b(r,theta,m=0)/r
```

# **Parameters**

- fl (\*) [real,out] :: Field for field lines
- **n\_r** [integer,in] :: No. of radial grid point
- n\_theta\_start [integer,in] :: No. of theta to start with
- n\_theta\_block [integer,in] :: Size of theta block
- **l\_ic** [logical,in] :: =true if inner core field

Called from store\_fields\_p(), store\_movie\_frame\_ic()

```
subroutine out_movie/get_b_surface (b_r, b_t, b_p, bcmb, n_theta_start, n_theta_block)
```

Upward continuation of laplacian field to Earths surface. Field is given by poloidal harmonic coefficients b at CMB. Spherical harmonic transforms of upward continued field to r/theta/phi vector components for all logitudes and latitude are returned in br/bt/bp. Note that this routine given the real components of the magnetic fields while other transforms in the code provide only:

```
r^{**}2 br, r^{**}2 sin(theta) bt, r^{**}2 sin(theta) bp
```

#### **Parameters**

- **b\_r** (*nrp*,\*) [real,out] :: Radial magnetic field in (phi,theta)-space
- **b t** (*nrp*,\*) [real,out] :: Latitudinal magnetic field
- **b\_p** (*nrp*,\*) [real,out] :: Azimuthal magnetic field.
- **bcmb** (*lm\_max*) [*complex*, *in*]
- n\_theta\_start [integer,in] :: No. of theta to start with
- n\_theta\_block [integer,in] :: Size of theta block

```
Called from store_fields_sur()
Call to fft thetab()
```

# 10.16.4 store movie IC.f90

#### Quick access

```
Routines store_movie_frame_ic()
```

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (1ffac()): Module containing the physical parameters

- horizontal\_data (dlh(), plm(), n\_theta\_cal2ord(), dplm(), o\_sin\_theta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_cond\_ic()): Module containing the logicals that control the run
- radial\_functions(r\_ic(), o\_r\_ic2(), o\_r\_ic(), r\_icb())
- blocking (nthetabs (), sizethetab (), nfs ()): Module containing blocking information
- fft\_jw(fft\_thetab()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- radial\_data(n\_r\_icb())
- truncation (n\_phi\_max(), lm\_maxmag(), n\_theta\_max(), minc(), n\_r\_ic\_maxmag(), lm\_max(), l\_max(), n\_r\_maxmag(), nrp(), n\_r\_ic\_max()): This module defines the grid points and the truncation
- legendre\_spec\_to\_grid(legtf())
- out\_movie(get\_fl())
- constants (one ()): module containing constants and parameters used in the code.
- leg\_helper\_mod(legprep\_ic())

#### **Variables**

# **Subroutines and functions**

```
subroutine out_movie_ic/store_movie_frame_ic (b, b_ic, db_ic, ddb_ic, aj_ic, dj_ic)
```

Controls storage of IC magnetic field in movie frame.

# **Parameters**

- **b** (lm maxmag,n r maxmag) [complex,in]
- **b\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **db\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **ddb\_ic** (*lm\_maxmag*,*n\_r\_ic\_maxmag*) [*complex*,*in*]
- aj\_ic (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **dj\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]

```
Called from output ()
```

```
Call to legprep_ic(), legtf(), fft_thetab(), get_fl()
```

# 10.16.5 out\_coeff.f90

# Description

This module contains the subroutines that calculate the Bcmb files and the [BIVIT]\_coeff\_r files

# **Quick access**

```
Routines write_coeff_r(), write_bcmb()
```

# **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- logic (l\_save\_out ()): Module containing the logicals that control the run

# **Variables**

# Subroutines and functions

Each call of this subroutine writes time and the poloidal magnetic potential coefficients b at the CMB up to degree and order l\_max\_cmb at the end of output file \$cmb\_file. The parameters l\_max\_cmb, minc and the number of stored coeffs. are written into the first line of \$cmb\_file. Each further set contains:

```
time,
real(b(1=0, m=0)), imag(b(1=0, m=0)),
real(b(1=1, m=0)), imag(b(1=1, m=0)),
```

Real and imaginary part of b(\*) for all orders m<=l are written for a specific degree l, then for the degrees l+1, l+2, l\_max\_cmb.

#### **Parameters**

- **time** [real,in] :: Time
- **b** (*ulm-llm*+1) [*complex*,*in*]
- **llm** [integer,in]
- **ulm** [integer,in] :: Poloidal field potential
- l\_max [integer,in,] :: Gives position of (l,m) coeff
- l\_max\_cmb [integer,inout] :: Max degree of output
- minc [integer,in] :: Basic wave-number
- $lm2 (l_max + 1, l_max + 1) [integer, in]$
- n\_cmb\_sets [integer,inout] :: Total no. of cmb sets,
- cmb\_file [character,in] :: Name of output file
- **n\_cmb\_file** [integer,in] :: Output unit for \$cmb\_file

Called from output(), fields\_average()

**subroutine** out\_coeff/write\_coeff\_r (time, w, dw, ddw, z, r, llm, ulm, l\_max, l\_max\_r, minc, lm2,  $n\_sets$ , file,  $n\_file$ , nvbs)

Each call of this subroutine writes time and the poloidal and toroidal coeffitients w,dw,z at a specific radius up to degree and order l\_max\_r at the end of output file \$file. If the input is magnetic field (nVBS=2) ddw is stored as well. If the input is entropy field (nVBS=3) only ddw=s is stored. The parameters l\_max\_r, minc, the number of stored coeffs and radius in the outer core are written into the first line of \$file. Each further set contains:

```
time,
real(w(l=0, m=0)), imag(w(l=0, m=0)),
real(w(l=1, m=0)), imag(w(l=1, m=0)),
...
real(dw(l=0, m=0)), imag(dw(l=0, m=0)),
real(dw(l=1, m=0)), imag(dw(l=1, m=0)),
...
real(z(l=0, m=0)), imag(z(l=0, m=0)),
real(z(l=1, m=0)), imag(z(l=1, m=0)),
...
real(ddw(l=0, m=0)), imag(ddw(l=0, m=0)),
real(ddw(l=1, m=0)), imag(ddw(l=1, m=0)),
real(ddw(l=1, m=0)), imag(ddw(l=1, m=0)),
```

Real and imaginary part of w(\*) for all orders  $m \le 1$  are written for a specific degree 1, then for the degrees 1+1, 1+2,  $1_max_r$ .

# **Parameters**

```
time [real,in] :: Time
w (ulm-llm+1) [complex,in]
dw (ulm-llm+1) [complex,in]
ddw (ulm-llm+1) [complex,in]
z (ulm-llm+1) [complex,in]
r [real,in] :: radius of coeffs
llm [integer,in]
ulm [integer,in] :: Toroidal field potential
l_max [integer,in,] :: Max degree of b(,)
l_max_r [integer,inout] :: Max degree of output
minc [integer,in] :: Basic wave-number
lm2 (l_max + 1,l_max + 1) [integer,in]
n_sets [integer,inout] :: Total no. of cmb sets,
file [character,in] :: Name of output file
n_file [integer,in] :: Output unit for $file
```

• **nvbs** [integer,in] :: True if output is flow

Called from output ()

# 10.16.6 store\_pot.f90

# **Description**

This module contains the subroutines that can be used to write unformatted fortran files that contain the flow/magnetic field potentials (in both Chebyshev and spectral space)

#### **Quick access**

```
Routines storepot(), storepotw()
```

#### **Needed modules**

- precision mod: This module controls the precision used in MagIC
- physical\_parameters (radratio(), sigma\_ratio(), prmag(), ra(), pr(), ek()): Module containing the physical parameters
- output\_data(tag()): This module contains the parameters for output control
- logic (l\_cond\_ic()): Module containing the logicals that control the run
- radial\_functions (i\_costf\_init(), d\_costf1\_ic\_init(), i\_costf1\_ic\_init(), d\_costf\_init())
- cosine\_transform(costf1())
- constants (half(), two()): module containing constants and parameters used in the code.
- lmloop\_data(ulm(), llm())
- truncation (lm\_max(), n\_r\_max(), n\_cheb\_max(), minc(), l\_max(), n\_r\_ic\_max(), n\_cheb\_ic\_max()): This module defines the grid points and the truncation
- communications (gather from lo to rank0())
- parallel\_mod (rank ()): This module contains the blocking information

# **Variables**

# Subroutines and functions

**subroutine** store pot mod/**storepot** (time, b, ai, b ic, ai ic, npotsets, root, omega ma, omega ic)

- time [real,in]
- **b** (lm\_max,n\_r\_max) [complex,in]
- aj (lm\_max,n\_r\_max) [complex,in]
- **b\_ic** (*lm\_max*,*n\_r\_ic\_max*) [*complex*,*in*]
- aj\_ic (lm\_max,n\_r\_ic\_max) [complex,in]
- **npotsets** [integer,inout]
- **root** [character,in]

- omega\_ma [real,in]
- omega\_ic [real,in]

Called from output ()

**subroutine** store\_pot\_mod/**storepotw**(*time*, *b*, *aj*, *b\_ic*, *aj\_ic*, *worka*, *workb*, *workc*, *npotsets*, *root*, *omega\_ma*, *omega\_ic*)

# **Parameters**

- time [real,in]
- **b** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **aj** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **b\_ic** (*ulm*-(*llm*)+1,*n\_r\_ic\_max*) [*complex*,*in*]
- **aj\_ic** (*ulm*-(*llm*)+1,*n\_r\_ic\_max*) [*complex*,*in*]
- worka (ulm-(llm)+1,n\_r\_max) [complex]
- workb (ulm-(llm)+1,n\_r\_max) [complex]
- **workc** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*]
- **npotsets** [integer,inout]
- root [character,in]
- omega\_ma [real,in]
- omega\_ic [real,in]

Called from fields average()

Call to gather\_from\_lo\_to\_rank0()

# 10.16.7 field\_average.f90

# **Description**

This module is used when one wants to store time-averaged quantities

# **Quick access**

```
Variables dw_ave_global, s_ave_global, s_ave, aj_ic_ave, db_ave_global, z_ave,
    z_ave_global, b_ave, aj_ave_global, w_ave_global, b_ic_ave, aj_ave, w_ave
Routines fields_average(), initialize_fields_average_mod()
```

- store\_pot\_mod (storepotw()): This module contains the subroutines that can be used to write unformatted fortran files that contain the flow/magnetic field potentials (in both Chebyshev and spectral space)
- output\_data(l\_max\_cmb(), tag(), nlf(), n\_graphs(), graph\_file(), n\_graph\_file(), log\_file()): This module contains the parameters for output control
- constants (one (), vol\_oc(), zero(), vol\_ic()): module containing constants and parameters used in the code.

- blocking (lmstopb(), nfs(), sizethetab(), lmstartb(), nthetabs(), lm2()): Module containing blocking information
- truncation: This module defines the grid points and the truncation
- spectra(spectrum\_temp(), spectrum())
- parallel\_mod (rank ()): This module contains the blocking information
- magnetic\_energy (get\_e\_mag())
- radial\_der (get\_drns()): Radial derivatives functions
- out\_coeff (write\_bcmb()): This module contains the subroutines that calculate the Bcmb files and the [BIVIT]\_coeff\_r files
- kinetic\_energy (get\_e\_kin())
- precision\_mod: This module controls the precision used in MagIC
- leg\_helper\_mod(legprep())
- horizontal\_data (d1h (), plm(), dplm()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_mag(), l\_save\_out(), l\_cond\_ic(), l\_heat(), l\_conv()): Module containing the logicals that control the run
- radial\_functions (drx(), d\_costf\_init(), i\_costf2\_ic\_init(), i\_costf\_init(), d\_costf1\_ic\_init(), i\_costf1\_ic\_init(), r(), d\_costf2\_ic\_init(), dr\_fac\_ic())
- fft\_jw: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- radial\_data(n\_r\_cmb())
- communications (get\_global\_sum(), gather\_from\_lo\_to\_rank0(), gt\_oc(), gather\_all\_from\_lo\_to\_rank0(),gt\_ic())
- legendre\_spec\_to\_grid(legtf())
- graphout\_mod(graphout(), graphout\_ic())
- lmloop\_data(ulm(), llm(), llmmag(), ulmmag())
- radial\_der\_even(get\_drns\_even(), get\_ddrns\_even())

# **Variables**

- fields\_average\_mod/**z\_ave\_global** (:) [complex,private/allocatable]
- fields\_average\_mod/**b\_ave** (:,:) [complex,private/allocatable]
- fields\_average\_mod/s\_ave\_global(:) [complex,private/allocatable]
- fields\_average\_mod/aj\_ic\_ave (:,:) [complex,private/allocatable]
- fields\_average\_mod/b\_ic\_ave (:,:) [complex,private/allocatable]
- fields\_average\_mod/w\_ave(:,:) [complex,private/allocatable]
- fields\_average\_mod/aj\_ave\_global(:) [complex,private/allocatable]
- fields\_average\_mod/**s\_ave** (:,:) [complex,private/allocatable]
- fields\_average\_mod/w\_ave\_global(:) [complex,private/allocatable]
- fields\_average\_mod/**z\_ave** (:,:) [complex,private/allocatable]

- fields\_average\_mod/**db\_ave\_global**(:) [complex,private/allocatable]
- fields\_average\_mod/dw\_ave\_global(:) [complex,private/allocatable]
- fields\_average\_mod/aj\_ave(:,:) [complex,private/allocatable]

# **Subroutines and functions**

# **Parameters**

- nave [integer,in] :: number for averaged time steps
- **l\_stop\_time** [logical,in] :: true if this is the last time step
- time\_passed [real,in] :: time passed since last log
- **time\_norm** [real,in] :: time passed since start of time loop
- omega\_ic [real,in]
- omega\_ma [real,in]
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]

This subroutine averages fields b and v over time.

- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **s** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- $\bullet \ \ \mathbf{b} \ (ulmmag\text{-}(llmmag)\text{+}1, n\_r\_maxmag) \ [complex, in] \\$
- **aj** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [*complex,in*]
- **b\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- aj\_ic (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]

# Called from output ()

```
Call to get_drns(), get_ddrns_even(), get_drns_even(), spectrum(),
    spectrum_temp(), get_e_kin(), get_e_mag(), graphout(),
    gather_all_from_lo_to_rank0(), gather_from_lo_to_rank0(),
    legprep(), legtf(), fft_thetab(), graphout_ic(), write_bcmb(),
    storepotw()
```

# 10.17 IO: RMS force balance, torsional oscillations, misc

# 10.17.1 RMS . £90

# Description

This module contains the global array used when RMS force balance is requested

#### **Quick access**

Variables advpolas2hint, mag2hint, lftor2hint, advpollmr, geo2hint, arcas2hint, dtbpolas2hint, advpol2hint, prelmr, diftoras2hint, dtbtor2hint, corpol2hint, arclmr, difpolas2hint, dtvpol2hint, corpolas2hint, dtbpol2hint, magas2hint, buoas2hint, diftor2hint, difpol2hint, geolmr, advtor2hint, dtvtoras2hint, dtbpollmr, maglmr, lfpolas2hint, difpollmr, cortor2hint, preas2hint, corpollmr, dtvpolas2hint, geoas2hint, advtoras2hint, buo2hint, arc2hint, dtvpollmr, lfpol2hint, pre2hint, dtvtor2hint, lftoras2hint, cortoras2hint, lfpollmr, dtbtoras2hint, buolmr

Routines zerorms(), initialize\_rms()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- truncation(lm\_max(), n\_r\_max(), n\_r\_maxmag(), lm\_maxmag()): This module defines the grid points and the truncation
- constants (zero ()): module containing constants and parameters used in the code.

#### **Variables**

- rms/dtvtor2hint (:,:) [real,allocatable/public]
- rms/lftor2hint(:)[real,allocatable/public]
- rms/lftoras2hint(:)[real,allocatable/public]
- rms/cortoras2hint(:)[real,allocatable/public]
- rms/dtbtor2hint (:,:) [real,allocatable/public]
- rms/magas2hint (:) [real,allocatable/public]
- rms/buolmr (:,:) [complex,allocatable/public]
- rms/preas2hint(:)[real,allocatable/public]
- rms/corpol2hint(:)[real,allocatable/public]
- rms/buo2hint (:) [real,allocatable/public]
- rms/buoas2hint (:) [real,allocatable/public]
- rms/geo2hint(:)[real,allocatable/public]
- rms/diftor2hint (:,:) [real,allocatable/public]
- rms/advpolas2hint (:) [real,allocatable/public]
- rms/difpolas2hint (:,:) [real,allocatable/public]
- rms/corpolas2hint (:) [real, allocatable/public]
- rms/mag2hint (:) [real,allocatable/public]
- rms/dtvpol2hint (:,:) [real,allocatable/public]
- rms/dtbpolas2hint (:,:) [real,allocatable/public]

- rms/corpollmr(:,:) [complex,allocatable/public]
- rms/difpollmr(:,:) [complex,allocatable/public]
- rms/cortor2hint (:) [real,allocatable/public]
- rms/arc2hint (:) [real,allocatable/public]
- rms/difpol2hint (:,:) [real,allocatable/public]
- rms/geolmr(:,:) [complex,allocatable/public]
- rms/geoas2hint (:) [real,allocatable/public]
- rms/advtor2hint(:)[real,allocatable/public]
- rms/dtbpol2hint(:,:) [real,allocatable/public]
- rms/dtvtoras2hint(:,:) [real,allocatable/public]
- rms/lfpol2hint (:) [real,allocatable/public]
- rms/lfpollmr (:,:) [complex,allocatable/public]
- rms/advpol2hint (:) [real,allocatable/public]
- rms/maglmr (:,:) [complex,allocatable/public]
- rms/dtbpollmr(:,:) [complex,allocatable/public]
- rms/dtvpollmr (:,:) [complex,allocatable/public]
- rms/lfpolas2hint (:) [real,allocatable/public]
- rms/arclmr(:,:) [complex,allocatable/public]
- rms/dtbtoras2hint(:,:) [real,allocatable/public]
- rms/dtvpolas2hint (:,:) [real,allocatable/public]
- rms/prelmr(:,:) [complex,allocatable/public]
- rms/pre2hint (:) [real,allocatable/public]
- rms/diftoras2hint(:,:) [real,allocatable/public]
- rms/arcas2hint (:) [real,allocatable/public]
- rms/advtoras2hint(:)[real,allocatable/public]
- rms/advpollmr(:,:) [complex,allocatable/public]

#### Subroutines and functions

```
subroutine rms/initialize_rms()
    Memory allocation
    Called from magic
subroutine rms/zerorms()
    Zeros integrals that are set in get_td, update_z, update_wp, update_b, dtVrms and dtBrms
    Called from output()
```

# 10.17.2 RMS\_helpers.f90

# **Description**

This module contains several useful subroutines required to compute RMS diagnostics

#### **Quick access**

```
Routines get_poltorrms(), get_ras(), get_paslm(), init_rnb(), hint2tor(),
hint2dpol(), hint2pol()
```

# **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- lmmapping (mappings())
- horizontal\_data(dlh(), osn1(), dplm(), plm()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- constants (one (), vol\_oc ()): module containing constants and parameters used in the code.
- init\_costf(init\_costf1())
- radial\_functions(r(), drx(), or2(), i\_costf\_init(), d\_costf\_init())
- blocking (st\_map(), 1m2()): Module containing blocking information
- useful (cc2real ()): library with several useful subroutines
- truncation(lm\_max(), n\_r\_max(), l\_max(), lm\_max\_dtb()): This module defines the grid points and the truncation
- integration (rint\_r()): Radial integration functions
- chebyshev\_polynoms\_mod(cheb\_grid())
- radial\_der (get\_dr()): Radial derivatives functions

# **Variables**

# **Subroutines and functions**

```
subroutine rms_helpers/get_paslm(tlm, bp, rt, nthetastart, sizethetablock)
```

Purpose of this subroutine is to calculated the axisymmetric phi component Bp of an axisymmetric toroidal field Tlm given in spherical harmonic space (1,m=0).

- tlm (lm\_max\_dtb) [complex,in] :: field in (l,m)-space for rT
- **bp** (\*) [real,out]
- rt [real,in] :: radius
- **nthetastart** [integer,in] :: first theta to be treated
- **sizethetablock** [integer,in] :: size of theta block

```
Called from dtbrms()
```

```
subroutine rms_helpers/get_poltorrms (pol, drpol, tor, polrms, torrms, polasrms, torasrms, map)
```

calculates integral PolRms=sqrt( Integral (pol^2 dV) ) calculates integral TorRms=sqrt( Integral (tor^2 dV) ) plus axisymmetric parts. integration in theta,phi by summation of spherical harmonics integration in r by using Chebycheff integrals The mapping map gives the mapping Im to l,m for the input arrays Pol,drPol and Tor Output: PolRms,TorRms,PolAsRms,TorAsRms

# **Parameters**

- pol (lm\_max,n\_r\_max) [complex,in] :: Poloidal field Potential
- **drpol** (*lm\_max,n\_r\_max*) [*complex,in*] :: Radial derivative of Pol
- tor (lm\_max,n\_r\_max) [complex,in] :: Toroidal field Potential
- **polrms** [real,out]
- torrms [real,out]
- polasrms [real,out]
- torasrms [real,out]
- map [mappings,in]

```
Called from dtbrms()
```

```
Call to cc2real(), rint r()
```

subroutine rms\_helpers/hint2dpol(dpol, lmstart, lmstop, pol2hint, polas2hint, map)

# **Parameters**

- **dpol** (*lm\_max*) [*complex,in*] :: Toroidal field Potential
- **Imstart** [integer,in]
- **Imstop** [integer,in]
- pol2hint [real,inout]
- polas2hint [real,inout]
- map [mappings,in]

Called from dtbrms(), dtvrms()

Call to cc2real()

**subroutine** rms helpers/**hint2pol** (pol, lb, ub, nr, lmstart, lmstop, pollmr, pol2hint, polas2hint, map)

- **pol** (ub-lb+1) [complex,in]
- **lb** [integer,in]
- **ub** [integer,in] :: Poloidal field Potential
- **nr** [integer,in]
- **Imstart** [integer,in]
- **Imstop** [integer,in]
- **pollmr** (*lm\_max*,*n\_r\_max*) [*complex*,*out*]

```
• pol2hint [real,inout]
```

- polas2hint [real,inout]
- map [mappings,in]

```
Called from updateb(), get_td(), updatewp()
```

Call to cc2real()

**subroutine** rms helpers/hint2tor(tor, lb, ub, nr, lmstart, lmstop, tor2hint, toras2hint, map)

# **Parameters**

- **tor** (ub-lb+1) [complex,in]
- **lb** [integer,in]
- **ub** [integer,in] :: Toroidal field Potential
- nr [integer,in]
- **Imstart** [integer,in]
- **lmstop** [integer,in]
- **tor2hint** [real,inout]
- toras2hint [real,inout]
- map [mappings,in]

```
Called from updateb(), get_td(), updatez()
```

Call to cc2real()

```
subroutine rms_helpers/get_ras (blm, br, rt, nthetastart, sizethetablock)
```

Purpose of this subroutine is to calculate the axisymmetric radial component Br of an axisymmetric ploidal field Blm given in spherical harmonic space (l,m=0).

# **Parameters**

- **blm** (*lm\_max\_dtb*) [*complex,in*] :: field in (l,m)-space for rT
- **br** (\*) [real,out]
- rt [real,in] :: radius
- **nthetastart** [integer,in] :: first theta to be treated
- sizethetablock [integer,in] :: last theta

Called from dtbrms()

```
subroutine rms_helpers/init_rnb (r, n_r_max, n_cheb_max, rcut, rdea, r2, n_r_max2, n_cheb_max2, ns, dr_fac2, i_costf_init2, ndi_costf1, d_costf_init2, ndd_costf1)
```

Prepares the usage of a cut back radial grid where nS points on both boundaries are discarded. The aim actually is to discard boundary effects, but just not considering the boundary grid points does not work when you also want radial derivatives and integrals. For these we use the Chebychev transform which needs are particular number of grid points so that the fast cosine transform can be applied. Therefor more than just 2 points have to be thrown away, which may make sense anyway.

# **Parameters**

• **r** (\*) [real,in]

```
• n_r_max [integer,in]
```

- n\_cheb\_max [integer,in]
- rcut [real,in]
- rdea [real,in]
- **r2** (\*) [real,out]
- n r max2 [integer,out]
- n\_cheb\_max2 [integer,out]
- **ns** [integer,out]
- **dr\_fac2** (\*) [real,out]
- i\_costf\_init2 (ndi\_costf1) [integer,out] :: info for transform
- ndi\_costf1 [integer,in]
- **d\_costf\_init2** (*ndd\_costf1*) [*real,out*] :: info for tranfor
- **ndd\_costf1** [integer,in]

Called from dtvrms()

Call to cheb\_grid(), init\_costf1()

# 10.17.3 out\_RMS.f90

#### **Quick access**

Routines dtbrms(), dtvrms()

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters(radratio(), prmag(), ek(), pr(), ra()): Module containing the physical parameters
- horizontal\_data (theta\_ord(), phi()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic (l\_corr(), l\_rmstest(), l\_conv(), l\_save\_out(), l\_conv\_nl(), l\_heat(), l\_mag\_lf()): Module containing the logicals that control the run
- radial\_der(get\_drns()): Radial derivatives functions
- radial\_functions (ndi\_costf1(), drx(), n\_r\_maxc(), i\_costf\_init(), rc(), rgrav(), ncut(), n\_cheb\_maxc(), d\_costf\_initc(), d\_costf\_init(), ndd\_costf1(), dr\_facc(), r(), i\_costf\_initc(), r\_cmb())
- blocking (st\_map(), lo\_map(), nfs(), nthetabs(), sizethetab(), lm2()): Module containing blocking information
- radial\_data(nrstop(), nrstart())
- truncation(n\_phi\_max(), lm\_max(), n\_r\_max(), n\_cheb\_max(), minc(), n\_theta\_max(), lm\_maxmag(), n\_r\_maxmag(), lm\_max\_dtb(), n\_r\_max\_dtb()): This module defines the grid points and the truncation

- communications (myallgather())
- dtb\_mod (tadvasrms(), padvrms(), pdifasrms(), pstrasrms(), tomeasrms(), tdifasrms(), tomelm(), tstrrms(), padvasrms(), tadvlm(), tstrasrms(), pstrrms(), tstrlm(), padvlm(), pdiflm(), tomerms(), pstrlm(), pdifrms(), tdiflm(), tadvrms(), tdifrms()): This module contains magnetic field stretching and advection terms plus a separate omegaeffect. It is used for movie output....
- parallel\_mod: This module contains the blocking information
- output\_data (n\_dtvasrms\_file(), n\_dtbrms\_file(), rdea(), n\_dtvrms\_file(), dtvrms\_file(), dtvrms\_file(), tag(), dtdrms\_file(), runid(), n\_dtdrms\_file()): This module contains the parameters for output control
- integration (rint\_r()): Radial integration functions
- constants (vol\_oc(), third(), pi(), half(), four(), zero()): module containing constants and parameters used in the code.
- num\_param(tscale()): Module containing numerical and control parameters
- rms (dtvtor2hint(), lftor2hint(), lftoras2hint(), cortoras2hint(), dtbtor2hint(), magas2hint(), buolmr(), preas2hint(), corpol2hint(), dtbpollmr(), buoas2hint(), geo2hint(), diftor2hint(), advpolas2hint(), difpolas2hint(), corpolas2hint(), mag2hint(), dtvpol2hint(), dtbpolas2hint(), corpollmr(), difpollmr(), cortor2hint(), arc2hint(), dtvpolas2hint(), geolmr(), geoas2hint(), advtor2hint(), dtbpol2hint(), dtvtoras2hint(), lfpol2hint(), lfpollmr(), advpol2hint(), mag1mr(), buo2hint(), dtvpollmr(), lfpolas2hint(), arclmr(), dtbtoras2hint(), difpol2hint(), prelmr(), pre2hint(), diftoras2hint(), arcas2hint(), advtoras2hint(), advpollmr()): This module contains the global array used when RMS force balance is requested
- rms\_helpers (get\_paslm(), hint2dpol(), get\_poltorrms(), get\_ras(), init\_rnb()): This module contains several useful subroutines required to compute RMS diagnostics

# **Variables**

# Subroutines and functions

subroutine out\_rms/dtvrms (time, nrms\_sets)

For testing RMS balance and determining the necessary values of rDea and rCut one can use the l\_RMStest=true options. In this case the poloidal and toroidal RMS dtV which also include the diffusion effects should be identical (as close as desired) to the RMS sum of forces stored in the Geo value and the Mag value, respectively. An additional tests is the Arc value which should be identical to the poloidal kinetic energy.

**Note:** The second test with the Arc value cannot work so easily in the anelastic version as the density enters now in the force balance. The first test should work, though.

### **Parameters**

- time [real,in]
- nrms\_sets [integer,inout]

Called from output ()

Call to myallgather(), init\_rnb(), get\_drns(), hint2dpol(), rint\_r()

# 10.17.4 dtB.f90

# **Description**

This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output.

#### **Quick access**

```
Variables tadvlmic_lmloc, tomelm, pdiflmic_lmloc, tadvlmic, padvlmic_lmloc, tadvlm_rloc, tstrrlm, tomelm_rloc, tdiflmic_lmloc, tstrlm, pdiflm_lmloc, pstrlm, tadvrlm_rloc, tstrlm_rloc, padvlm, pdiflmic, pdiflm, tadvlm, tdiflm_lmloc, padvlm_rloc, pstrlm_rloc, tadvrlm, tomerlm_rloc, tomerlm, tdiflmic, tstrrlm_rloc, padvlmic, tdiflm, tomerms, pstrasrms, pdifasrms, padvrms, tomeasrms, tdifrms, tadvrms, tstrasrms, tstrrms, padvasrms, pdifrms, tadvasrms, pstrrms, tdifasrms
```

```
Routines get_dh_dtblm(), get_dtblmfinish(), initialize_dtb_mod(), get_dtblm(), dtb_gather_rloc_on_rank0()
```

- precision\_mod: This module controls the precision used in MagIC
- physical parameters (o sr(), opm()): Module containing the physical parameters
- horizontal\_data (cosn2(), dlh(), osn1(), d\_lp1(), dphi(), dtheta1a(), osn2(), dtheta1s(), hdif\_b()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_dtrmagspec(), l\_cond\_ic()): Module containing the logicals that control the run
- radial\_functions (drx(), o\_r\_ic(), or1(), d\_costf\_init(), i\_costf\_init(), or2(), dllambda(), orho1(), lambda())
- blocking (st\_map(), 121mas(), 10\_map(), nfs(), 1m21(), 1mp21mpa(), 1mp21mps(), 1m2m(), 1m21mp()): Module containing blocking information
- fft\_jw: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- legendre\_grid\_to\_spec(legtf2(), legtf3())
- radial\_data(nrstop(), nrstart())
- truncation (ldtbmem(), n\_r\_max(), n\_r\_ic\_maxmag(), n\_r\_max\_dtb(), nrp(), n\_phi\_max(), lm\_max(), n\_cheb\_max(), l\_max(), n\_r\_maxmag(), n\_r\_ic\_max(), lm\_max\_dtb(), n\_r\_ic\_max\_dtb()): This module defines the grid points and the truncation
- communications(gt\_ic(), gather\_all\_from\_lo\_to\_rank0(), gt\_oc())

- parallel\_mod: This module contains the blocking information
- radial\_spectra
- constants (two ()): module containing constants and parameters used in the code.
- radial\_der (get\_drns ()): Radial derivatives functions
- !mloop data(ulm(), llm(), llmmag(), ulmmag())

# **Variables**

- dtb\_mod/pstrasrms [real, public]
- dtb\_mod/pstrlm(:,:) [complex,allocatable/public]
- dtb\_mod/tadvrlm(:,:) [complex,allocatable/public]
- dtb\_mod/pdiflmic(:,:) [complex,allocatable/public]
- dtb\_mod/tstrrms [real,public]
- dtb\_mod/padvlmic\_lmloc(:,:) [complex,allocatable/public]
- dtb\_mod/tstrasrms [real,public]
- dtb\_mod/tadvlmic(:,:) [complex,allocatable/public]
- dtb\_mod/pdiflm\_lmloc(:,:) [complex,allocatable/public]
- dtb\_mod/tstrlm\_rloc(:,:) [complex,allocatable/public]
- dtb\_mod/tomerlm(:,:) [complex,allocatable/public]
- dtb\_mod/**pdifasrms** [real,public]
- dtb\_mod/tdiflm\_lmloc(:,:) [complex,allocatable/public]
- dtb\_mod/padvasrms [real, public]
- dtb\_mod/tadvlm(:,:) [complex,allocatable/public]
- dtb\_mod/tadvlmic\_lmloc(:,:) [complex,allocatable/public]
- dtb\_mod/padvlm(:,:) [complex,allocatable/public]
- dtb mod/pdiflm(:,:) [complex,allocatable/public]
- dtb\_mod/tomerms [real, public]
- dtb\_mod/tomelm\_rloc(:,:) [complex,allocatable/public]
- dtb\_mod/tadvrlm\_rloc(:,:) [complex,allocatable/public]
- dtb\_mod/tadvlm\_rloc(:,:) [complex,allocatable/public]
- dtb\_mod/tdifrms [real,public]
- dtb\_mod/tadvasrms [real,public]
- dtb\_mod/tomeasrms [real,public]
- dtb\_mod/padvlmic(:,:) [complex,allocatable/public]
- dtb\_mod/tdiflmic(:,:) [complex,allocatable/public]
- dtb\_mod/tdifasrms [real,public]
- dtb mod/pstrrms[real,public]

- dtb\_mod/pdiflmic\_lmloc(:,:) [complex,allocatable/public]
- dtb\_mod/pdifrms [real,public]
- dtb\_mod/tadvrms [real,public]
- dtb\_mod/tstrrlm(:,:) [complex,allocatable/public]
- dtb\_mod/tdiflmic\_lmloc(:,:) [complex,allocatable/public]
- dtb\_mod/padvrms [real,public]
- dtb\_mod/tstrrlm\_rloc(:,:) [complex,allocatable/public]
- dtb\_mod/tomelm(:,:) [complex,allocatable/public]
- dtb\_mod/pstrlm\_rloc(:,:) [complex,allocatable/public]
- dtb\_mod/tomerlm\_rloc(:,:) [complex,allocatable/public]
- dtb\_mod/tstrlm(:,:) [complex,allocatable/public]
- dtb\_mod/padvlm\_rloc(:,:) [complex,allocatable/public]
- dtb\_mod/tdiflm(:,:) [complex,allocatable/public]

# **Subroutines and functions**

Called from magic

subroutine dtb\_mod/dtb\_gather\_rloc\_on\_rank0()

MPI communicators for dtB outputs

Called from get dtblmfinish()

subroutine dtb\_mod/get\_dtblm (nr, vr, vt, vp, br, bt, bp, n\_theta\_start, n\_theta\_block, btvrlm, bpvrlm, brvtlm, brvplm, btvplm, bpvtlm, brvzlm, btvzctlm, btvpcotlm, btvpcotlm, btvpsn2lm, btvzsn2lm, btvzsn2lm)

- **nr** [integer,in]
- **vr** (*nrp*,*nfs*) [*real*,*in*]
- **vt** (*nrp*,*nfs*) [*real*,*in*]
- **vp** (*nrp*,*nfs*) [*real*,*in*]
- **br** (*nrp*,*nfs*) [real,in]
- **bt** (*nrp*,*nfs*) [*real*,*in*]
- **bp** (*nrp*,*nfs*) [*real*,*in*]
- n\_theta\_start [integer,in]
- n\_theta\_block [integer,in]
- btvrlm (\*) [complex,out]
- **bpvrlm** (\*) [complex,out]
- brvtlm (\*) [complex,out]

```
• brvplm (*) [complex,out]
```

- **btvplm** (\*) [complex,out]
- **bpvtlm** (\*) [complex,out]
- **brvzlm** (\*) [complex,out]
- **btvzlm** (\*) [complex,out]
- **btvpcotlm** (\*) [complex,out]
- **bpvtcotlm** (\*) [complex,out]
- **btvzcotlm** (\*) [complex,out]
- btvpsn2lm (\*) [complex,out]
- **bpvtsn2lm** (\*) [complex,out]
- btvzsn2lm (\*) [complex,out]

 $\textbf{Called from } \texttt{do\_iteration\_thetablocking\_seq()}, \textit{do\_iteration\_thetablocking\_openmp()}$ 

Call to fft\_thetab(), legtf3(), legtf2()

# **Parameters**

- time [real,in]
- n\_time\_step [integer,in]
- omega ic [real,in]
- **b** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **ddb** (*ulmmag-(llmmag*)+1,*n\_r\_maxmag*) [*complex*,*in*]
- **aj** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- $\mathbf{dj}$  (ulmmag-(llmmag)+1, $n_r$ \_maxmag) [complex,in]
- $\bullet \ \mathbf{ddj} \ (ulmmag \hbox{-} (llmmag) \hbox{+} 1, n\_r\_maxmag) \ [complex, in] \\$
- **b\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- **db\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- **ddb\_ic** (*ulmmag-(llmmag*)+1,*n\_r\_ic\_maxmag*) [*complex*,*in*]
- aj\_ic (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- **dj\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- **ddj\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]

# Called from output ()

Call to dtb\_gather\_rloc\_on\_rank0(), get\_drns(), gather\_all\_from\_lo\_to\_rank0(),
 rbrspec(), rbpspec()

**subroutine** dtb\_mod/**get\_dh\_dtblm** (*nr*, *btvrlm*, *bpvrlm*, *brvtlm*, *brvplm*, *btvplm*, *bpvtlm*, *btvzcotlm*, *btvpsn2lm*, *btvpsn2lm*, *btvzsn2lm*)

Purpose of this routine is to calculate theta and phi derivative related terms of the magnetic production and advection terms and store them.

# **Parameters**

- **nr** [integer,in]
- **btvrlm** (\*) [complex,in]
- **bpvrlm** (\*) [complex,in]
- **brvtlm** (\*) [complex,in]
- **brvplm** (\*) [complex,in]
- btvplm (\*) [complex,in]
- **bpvtlm** (\*) [complex,in]
- brvzlm (\*) [complex,in]
- **btvzlm** (\*) [complex,in]
- btvpcotlm (\*) [complex,in]
- **bpvtcotlm** (\*) [complex,in]
- btvzcotlm (\*) [complex,in]
- btvpsn2lm (\*) [complex,in]
- bpvtsn2lm (\*) [complex,in]
- btvzsn2lm (\*) [complex,in]

**Called from** do\_iteration\_thetablocking\_seq(), do\_iteration\_thetablocking\_openmp()

# 10.17.5 out dtB frame.f90

#### **Quick access**

```
Routines write_dtb_frame(), lm2pt(), get_dtb(), get_bpol(), get_btor()
```

- precision\_mod: This module controls the precision used in MagIC
- horizontal\_data (d\_lp1(), osn1(), n\_theta\_cal2ord(), dplm(), costheta(), dlh(), dphi(), plm(), sintheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_cond\_ic()): Module containing the logicals that control the run
- radial\_functions(r\_ic(), drx(), d\_costfl\_ic\_init(), r(), i\_costf\_init(), r\_icb(), i\_costfl\_ic\_init(), d\_costfl\_ic\_init(), dr\_fac\_ic(), orl(), d\_costf\_init(), i\_costfl\_ic\_init())
- blocking (lm2m(), nfs(), lm2l(), nthetabs(), sizethetab(), lm2()): Module containing blocking information
- fft\_jw: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- movie\_data (n\_movie\_fields\_ic(), n\_movie\_fields(), n\_movie\_file(), n\_movie\_type(), n\_movie\_surface(), n\_movie\_field\_type(), n\_movie\_const(), movie\_const())

- truncation: This module defines the grid points and the truncation
- dtb\_mod(tstrlm(), tomelm(), padvlm(), pdiflm(), pstrlm(), pdiflmic(), tadvlmic(), padvlmic(), tdiflmic(), tadvlm(), tdiflm()): This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output....
- radial\_der(get\_drns()): Radial derivatives functions
- constants (one (), ci (), zero ()): module containing constants and parameters used in the code.
- radial\_der\_even(get\_drns\_even())

### **Variables**

#### Subroutines and functions

```
subroutine out_dtb_frame/write_dtb_frame(n_movie, b, db, aj, dj, b_ic, db_ic, aj_ic, dj_ic)
```

Controls output of specific movie frames related to magnetic field production and diffusion.

### **Parameters**

- n\_movie [integer,in]
- **b** (lm\_maxmag,n\_r\_maxmag) [complex,in]
- **db** (lm\_maxmag,n\_r\_maxmag) [complex,in]
- **aj** (lm\_maxmag,n\_r\_maxmag) [complex,in]
- **dj** (lm\_maxmag,n\_r\_maxmag) [complex,in]
- **b\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **db\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **aj\_ic** (*lm\_maxmag*,*n\_r\_ic\_maxmag*) [*complex*,*in*]
- **dj\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]

```
Called from write_movie_frame()
```

**subroutine** out\_dtb\_frame/**get\_dtb** (dtb, dtblm, dimb1, dimb2, n\_r, n\_theta\_start, n\_theta\_block, l\_ic)

### **Parameters**

- **dtb** (\*) [real,out]
- **dtblm** (dimb1,dimb2) [complex,in]
- dimb1 [integer, in, ]
- dimb2 [integer,in,]
- n\_r [integer,in] :: No. of radial grid point
- n\_theta\_start [integer,in] :: No. of theta to start with
- n theta block [integer,in] :: Size of theta block
- 1 ic [logical,in] :: =true if inner core field

Called from write\_dtb\_frame()

```
subroutine out dtb frame/get bpol (pollm, dpollm, br, bt, bp, rt, n theta start, n theta block, lic)
```

Purpose of this subroutine is to calculate the components Br, Bt, and Bp of the poloidal magnetic field PolLM (l,m space) at the radial grid point r=rT and the block of theta grid points from n\_theta=n\_theta\_start to n\_theta=n\_theta\_start+n\_theta\_block-1 and for all phis. For lIC=.true. the inner core field is calculated, to get the IC field for a conducting inner core PolLM has to be the poloidal field at the ICB.

#### **Parameters**

```
pollm (lm_max) [complex,in] :: field in (l,m)-space for rT
dpollm (lm_max) [complex,in] :: dr field in (l,m)-space for rT
br (nrp,*) [real,out]
bt (nrp,*) [real,out]
tr [real,in] :: radius
n_theta_start [integer,in] :: first theta to be treated
n_theta_block [integer,in] :: last theta
lic [logical,in] :: true for inner core, special rDep!
Called from write_dtb_frame()
Call to fft_thetab()
```

**subroutine** out\_dtb\_frame/**get\_btor** (*tlm*, *bt*, *bp*, *rt*, *n\_theta\_start*, *n\_theta\_block*, *lic*)

Purpose of this subroutine is to calculate the components Bt and Bp of the toroidal magnetic field Tlm (in l,m space) at the radial grid point r=rT and the block of theta grid points from n\_theta=n\_theta\_start to n\_theta=n\_theta\_start+n\_theta\_block-1 and for all phis. For lIC=.true. the inner core field is calculated, to get the IC field for a conducting inner core Plm has to be the toroidal field at the ICB.

## **Parameters**

```
tlm (lm_max) [complex,in] :: field in (l,m)-space for rT
bt (nrp,*) [real,out]
bp (nrp,*) [real,out]
rt [real,in] :: radius
n_theta_start [integer,in] :: first theta to be treated
n_theta_block [integer,in] :: last theta
lic [logical,in] :: true for inner core, special rDep!
Called from write_dtb_frame()
Call to fft_thetab()
```

subroutine out\_dtb\_frame/lm2pt (alm, aij, rt, nthetastart, lic, lrcomp)

Spherical harmonic transform from alm(l,m) to aij(phi,theta) Radial field components are calculated for lrComp=.true. Done within the range [n\_theta\_min,n\_theta\_min+n\_theta\_block-1] Used only for graphic output.

### **Parameters**

```
• alm (*) [complex,in] :: field in (l,m)-space
```

- aij (nrp,\*) [real,out] :: field in (theta,phi)-space
- rt [real,in]
- **nthetastart** [integer,in] :: first theta to be treated
- **lic** [logical,in] :: true for inner core, extra factor!
- **Ircomp** [logical,in] :: true for radial field components

```
Called from write_dtb_frame()
Call to fft_thetab()
```

### 10.17.6 TO. £90

### **Description**

This module contains information for TO calculation and output

#### **Quick access**

```
Variables dzddvplmr_rloc, bpzas, bszas_rloc, dzstrlmr, v2as, bzpdas, bspas_rloc, bs2as, bpzas_rloc, bspas, bpsdas, bszas, dzdvplmr_rloc, dzrstrlmr_rloc, bspdas_rloc, bzpdas_rloc, dzastrlmr, bs2as_rloc, dzrstrlmr, bpzdas_rloc, dzcorlmr_rloc, ddzasl, dzddvplmr, dzlflmr, dzcorlmr, bpsdas_rloc, bspdas, dzstrlmr_rloc, dzlflmr_rloc, bpzdas, v2as_rloc, dzastrlmr_rloc, dzdvplmr
```

```
Routines gettofinish(), initialize_to(), gettonext(), to_gather_rloc_on_rank0(), getto()
```

### **Needed modules**

- precision mod: This module controls the precision used in MagIC
- physical\_parameters (kbotv(), corfac(), ktopv()): Module containing the physical parameters
- horizontal\_data(hdif\_v(), costheta(), dlh(), dthetala(), dthetals(), sintheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- constants (one (), two ()): module containing constants and parameters used in the code.
- radial\_functions(dbeta(), or4(), orho1(), or1(), r(), or3(), or2(), beta())
- blocking (nfs(), 1m2()): Module containing blocking information
- legendre\_grid\_to\_spec(legtfas2())
- radial\_data(nrstop(), n\_r\_cmb(), nrstart())
- truncation (n\_theta\_maxstr(), n\_phi\_maxstr(), n\_r\_maxstr(), l\_max(), nrp()): This module defines the grid points and the truncation
- parallel\_mod: This module contains the blocking information

- logic (l\_mag(), lverbose()): Module containing the logicals that control the run
- lmloop\_data(llmmag(), ulmmag())

#### **Variables**

- torsional\_oscillations/dzastrlmr(:,:) [real,allocatable/public]
- torsional\_oscillations/bszas\_rloc(:,:) [real, allocatable/public]
- torsional\_oscillations/bpzdas\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/**bspas** (:,:) [real,allocatable/public]
- torsional\_oscillations/bpsdas(:,:) [real,allocatable/public]
- torsional\_oscillations/dzstrlmr(:,:) [real,allocatable/public]
- torsional\_oscillations/v2as(:,:) [real,allocatable/public]
- torsional\_oscillations/bpzas\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzlflmr(:,:) [real,allocatable/public]
- torsional\_oscillations/bspdas(:,:) [real,allocatable/public]
- torsional\_oscillations/bszas(:,:) [real,allocatable/public]
- torsional\_oscillations/dzddvplmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzstrlmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/ddzasl(:,:) [real,allocatable/public]
- torsional\_oscillations/bzpdas(:,:) [real,allocatable/public]
- torsional\_oscillations/bzpdas\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/bpzas(:,:) [real,allocatable/public]
- torsional\_oscillations/dzlflmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/bpzdas(:,:) [real,allocatable/public]
- torsional\_oscillations/bs2as\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzcorlmr(:,:) [real,allocatable/public]
- torsional\_oscillations/bspdas\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzastrlmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzrstrlmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzdvplmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzcorlmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/bspas\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/bpsdas\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzrstrlmr(:,:) [real,allocatable/public]
- torsional\_oscillations/dzdvplmr(:,:) [real,allocatable/public]
- torsional\_oscillations/bs2as(:,:) [real,allocatable/public]
- torsional\_oscillations/dzddvplmr(:,:) [real,allocatable/public]

• torsional\_oscillations/v2as\_rloc(:,:) [real,allocatable/public]

### Subroutines and functions

Called from magic

```
subroutine torsional_oscillations/initialize_to()
   Allocate the memory needed
```

**subroutine** torsional\_oscillations/**getto** (vr, vt, vp, cvr, dvpdr, br, bt, bp, cbr, cbt, bslast, bplast, bzlast, dzrstrlm, dzastrlm, dzcorlm, dzlflm, dtlast, nr, nthetastart, nthetablocksize)

This program calculates various axisymmetric linear and nonlinear variables for a radial grid point nR and a theta-block. Input are the fields vr,vt,vp,cvr,dvpdr Output are linear azimuthally averaged field VpAS (flow phi component), VpAS2 (square of flow phi component), V2AS (V\*V), and Coriolis force Cor. These are give in (r,theta)-space. Also in (r,theta)-space are azimuthally averaged correlations of non-axisymmetric flow components and the respective squares: Vsp=Vs\*Vp,Vzp,Vsz,VspC,VzpC,VszC. These are used to calulcate the respective correlations and Reynolds stress. In addition three output field are given in (lm,r) space: dzRstrLMr,dzAstrLMr,dzCorLM,dzLFLM.

These are used to calculate the total Reynolds stress, advection and viscous stress later. Their calculation retraces the calculations done in the time-stepping part of the code.

- **vr** (*nrp*,*nfs*) [real,in]
- **vt** (*nrp*,*nfs*) [*real*,*in*]
- **vp** (*nrp*,*nfs*) [real,in]
- cvr (nrp,nfs) [real,in]
- **dvpdr** (*nrp*,*nfs*) [real,in]
- **br** (*nrp*,*nfs*) [*real*,*in*]
- **bt** (nrp,nfs) [real,in]
- **bp** (*nrp*,*nfs*) [real,in]
- **cbr** (*nrp*,*nfs*) [real,in]
- **cbt** (*nrp*,*nfs*) [*real*,*in*]
- **bslast** (*n\_phi\_maxstr*,*n\_theta\_maxstr*,*nrstop-*(*nrstart*)+1) [real,in]
- **bplast** (*n\_phi\_maxstr*,*n\_theta\_maxstr*,*nrstop-*(*nrstart*)+1) [real,in]
- **bzlast** (n\_phi\_maxstr,n\_theta\_maxstr,nrstop-(nrstart)+1) [real,in]
- **dzrstrlm** (*l\_max*+2) [real,out]
- **dzastrlm** (*l\_max*+2) [real,out]
- **dzcorlm** (*l\_max*+2) [real,out]
- **dzlflm** (*l\_max*+2) [*real*, *out*]
- **dtlast** [real,in] :: last time step
- **nr** [integer,in] :: radial grid point

- **nthetastart** [integer,in] :: theta block
- nthetablocksize [integer,in]

Called from do\_iteration\_thetablocking\_seq(), do\_iteration\_thetablocking\_openmp()
Call to legtfas2()

Preparing TO calculation by storing flow and magnetic field contribution to build time derivative.

### **Parameters**

- **zas** (*l\_max*+1) [real,in]
- **br** (*nrp*,*nfs*) [real,in]
- **bt** (*nrp*,*nfs*) [*real*,*in*]
- **bp** (*nrp*,*nfs*) [*real*,*in*]
- **ltonext** [logical,in]
- ltonext2 [logical,in]
- **dt** [real,in]
- dtlast [real,in]
- **nr** [integer,in]
- **nthetastart** [integer,in]
- nthetablocksize [integer,in]
- **bslast** (*n\_phi\_maxstr*,*n\_theta\_maxstr*,*nrstop*-(*nrstart*)+1) [real,out]
- **bplast** (*n\_phi\_maxstr*,*n\_theta\_maxstr*,*nrstop-*(*nrstart*)+1) [real,out]
- **bzlast** (*n\_phi\_maxstr*,*n\_theta\_maxstr*,*nrstop-*(*nrstart*)+1) [real,out]

Called from do\_iteration\_thetablocking\_seq(), do\_iteration\_thetablocking\_openmp()

- **nr** [integer,in]
- dtlast [real,in]
- **zas** (*l\_max*+1) [*real,in*]
- **dzas** (*l\_max*+1) [real,in]
- **ddzas** (*l\_max*+1) [*real,in*]
- **dzrstrlm** (*l\_max*+2) [real,in]
- dzastrlm (l\_max+2) [real,in]
- **dzcorlm** (*l\_max*+2) [*real,in*]
- **dzlflm** (*l\_max*+2) [real,in]

Called from do\_iteration\_thetablocking\_seq(), do\_iteration\_thetablocking\_openmp()

subroutine torsional\_oscillations/to\_gather\_rloc\_on\_rank0()

MPI communicators for TO outputs

Called from outto()

# 10.17.7 TO\_helpers.f90

### **Description**

This module contains several helpful subroutines used in the TO calculations

### **Quick access**

```
Routines getastr(), get_pas(), getpastr()
```

### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- constants (one (), half (), two ()): module containing constants and parameters used in the code.
- horizontal\_data(osn1(), dplm()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- truncation (1\_max()): This module defines the grid points and the truncation
- blocking (1m2()): Module containing blocking information

# Variables

### **Subroutines and functions**

- **fz** (\*) [real,out]
- flmn (lmmax,\*) [real,in]
- nzmax [integer,in]
- nzmaxa [integer,in,]
- **lmmax** [integer,in,]
- lmax [integer,in]
- rmin [real,in]
- rmax [real,in]
- nchebmax [integer,in]
- rz (0.5 \* nzmaxa + 1.0) [real, in]

```
• dplm (lmmax,0.5 * nzmaxa + 1.0) [real,in]
```

• osints (0.5 \* nzmaxa + 1.0) [real,in]

Called from outto(), outpv()

subroutine to\_helpers/get\_pas (tlm, bp, rt, nthetastart, sizethetablock)

Purpose of this subroutine is to calculate the axisymmetric phi component Bp of an axisymmetric toroidal field Tlm given in spherical harmonic space (l,m=0).

### **Parameters**

- tlm (\*) [real,in] :: field in (l,m)-space for rT
- **bp** (\*) [real,out]
- **rt** [real,in] :: radius
- **nthetastart** [integer,in] :: first theta to be treated
- **sizethetablock** [integer,in] :: size of theta block

Called from outto()

subroutine to\_helpers/getastr (fz, flmn, nzmax, nzmaxa, lmmax, lmax, rmin, rmax, nchebmax, rz, plm)

Calculates function value at radii rZ(nZmax) and colatitudes for which Plm(theta) is given from the spherical harmonic/Chebychev coefficients of an axisymmetric function (order=0).

### **Parameters**

- **fz** (\*) [real,out]
- flmn (lmmax,\*) [real,in]
- nzmax [integer,in]
- nzmaxa [integer,in,]
- **lmmax** [integer,in,]
- lmax [integer,in]
- rmin [real,in]
- rmax [real,in]
- nchebmax [integer,in]
- rz (0.5 \* nzmaxa + 1.0) [real, in]
- **plm** (lmmax, 0.5 \* nzmaxa + 1.0) [real, in]

Called from outto()

# 10.17.8 out\_TO.f90

### Quick access

```
Variables vpm, osints, astrm, lfm, dplms, strm, corm, clm, plms, rz, rstrm, dvpm, zz, d_costf_initz, nzmaxs, i_costf_initz, lmmaxs
```

Routines outto(), initialize\_outto\_mod()

### **Needed modules**

- physical\_parameters(radratio(), prmag(), ra(), pr(), ek(), lffac()): Module containing the physical parameters
- output\_data (zdens(), tag(), nzmaxa(), runid(), n\_log\_file(), nsmaxa(), sdens(), log\_file()): This module contains the parameters for output control
- constants (vol\_oc(), two(), pi(), one(), half(), four()): module containing constants and parameters used in the code.
- blocking (sizethetab(), st\_map(), nthetabs(), nfs()): Module containing blocking information
- useful (logwrite()): library with several useful subroutines
- plms\_theta(plm\_theta())
- truncation(n\_phi\_max(), lm\_max(), n\_r\_max(), n\_r\_maxstr(), minc(), n\_theta\_max(), lstressmem(), n\_theta\_maxstr(), l\_max()): This module defines the grid points and the truncation
- integration(rint\_r()): Radial integration functions
- parallel\_mod (rank ()): This module contains the blocking information
- to\_helpers(getastr(), get\_pas(), getpastr()): This module contains several helpful subroutines used in the TO calculations
- precision\_mod: This module controls the precision used in MagIC
- horizontal\_data (theta\_ord(), phi(), gauss(), sintheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_save\_out(), lverbose()): Module containing the logicals that control the run
- radial\_functions (drx(), r\_cmb(), d\_costf\_init(), i\_costf\_init(), r\_icb(), r(), orhol())
- legendre\_grid\_to\_spec(legtfas2(), legtfas())
- torsional\_oscillations (bszas(), bpzdas(), dzcorlmr(), dzastrlmr(), dzstrlmr(), bspas(), v2as(), bpsdas(), to\_gather\_rloc\_on\_rank0(), bzpdas(), dzrstrlmr(), dzdvplmr(), dzrstrlmr\_rloc(), bpzas(), bs2as(), dzddvplmr(), dzlflmr(), bspdas()): This module contains information for TO calculation and output
- communications (gather\_all\_from\_lo\_to\_rank0(), gt\_oc())
- charmanip (dble2str()): This module contains several useful routines to manipule character strings
- chebint\_mod(chebintinit(), chebint())
- cosine transform(costf1())
- num\_param(tscale()): Module containing numerical and control parameters
- lmloop\_data(ulm(), llm())

# **Variables**

- outto\_mod/dvpm (:,:) [real,private/allocatable]
- outto\_mod/corm(:,:) [real,private/allocatable]
- outto\_mod/clm(:,:) [real,private/allocatable]

- outto\_mod/plms (:,:,:) [real,private/allocatable]
- outto\_mod/**vpm**(:,:) [real,private/allocatable]
- outto\_mod/**dplms** (:,:,:) [real,private/allocatable]
- outto\_mod/zz(:,:) [real,private/allocatable]
- outto mod/rz(:,:) [real,private/allocatable]
- outto mod/d costf initz(:,:) [real,private/allocatable]
- outto\_mod/strm(:,:) [real,private/allocatable]
- outto\_mod/lmmaxs[integer,private]
- outto\_mod/osints(:,:) [real,private/allocatable]
- outto\_mod/lfm(:,:) [real,private/allocatable]
- outto\_mod/astrm(:,:) [real,private/allocatable]
- outto\_mod/i\_costf\_initz (:,:) [integer,private/allocatable]
- outto\_mod/rstrm(:,:) [real,private/allocatable]
- outto\_mod/nzmaxs (:) [integer,private/allocatable]

#### Subroutines and functions

```
subroutine outto_mod/initialize_outto_mod()
```

Called from magic

**subroutine** outto\_mod/**outto** (time, n\_time\_step, ekin, ekintas, noutfile, noutfile2, tofilenhs, tofileshs, mov-file, tayfile, ntosets, ntormssets, ltomov, ltorms, ltozwrite, z, omega ic, omega ma)

Output of axisymmetric zonal flow, its relative strength, its time variation, and all forces acting on it. The slowest part in the TO process is the repetitious calculation of plms by subroutine plm\_theta. They are needed in getAStr and getPAStr when I transform on the cylindrical grid. The necessary plms could simply be calculated one and then be stored for later use!

- time [real,in]
- n\_time\_step [integer,in]
- ekin [real,in]
- ekintas [real,in]
- **noutfile** [integer,in]
- noutfile2 [integer,in]
- tofilenhs [character,in]
- tofileshs [character,in]
- movfile [character,in]
- tayfile [character,in]
- **ntosets** [integer,inout]

- **ntomovsets** [integer,inout]
- **ntormssets** [integer,inout]
- **Itomov** [logical,in]
- **Itorms** [logical,inout]
- **ltozwrite** [logical,inout]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- omega\_ic [real,in]
- omega\_ma [real,in]

### Called from output ()

# 10.17.9 radial\_spectra.f90

### **Quick access**

```
Routines rbpspec(), rbrspec()
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- lmmapping (mappings())
- horizontal\_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_cond\_ic()): Module containing the logicals that control the run
- $radial\_functions(r\_ic(), or2(), r\_icb())$
- blocking (st\_map()): Module containing blocking information
- useful (cc2real ()): library with several useful subroutines
- radial\_data(n\_r\_icb())
- truncation(lm\_max(), n\_r\_max(), l\_max(), n\_r\_tot(), n\_r\_ic\_max()): This module defines the grid points and the truncation
- output\_data(tag()): This module contains the parameters for output control
- constants (one (), half (), four (), pi ()): module containing constants and parameters used in the code.
- num\_param (escale()): Module containing numerical and control parameters

### **Variables**

### **Subroutines and functions**

**subroutine** radial\_spectra/**rbrspec** (*time*, *pol*, *polic*, *fileroot*, *lic*, *map*)

#### **Parameters**

- time [real,in]
- **pol** (*lm\_max*,*n\_r\_max*) [*complex*,*in*]
- polic (lm\_max,n\_r\_ic\_max) [complex,in]
- **fileroot** [character,in]
- lic [logical,in]
- map [mappings,in]

```
Called from get_dtblmfinish(), output()
```

Call to cc2real()

subroutine radial\_spectra/rbpspec (time, tor, toric, fileroot, lic, map)

Called from rank0, map gives the lm order of Tor and TorIC

#### **Parameters**

- time [real,in]
- **tor** (*lm\_max*,*n\_r\_max*) [*complex*,*in*]
- **toric** (*lm\_max*,*n\_r\_ic\_max*) [*complex*,*in*]
- **fileroot** [character,in]
- lic [logical,in]
- map [mappings,in]

```
Called from get_dtblmfinish(), output()
```

Call to cc2real()

### 10.17.10 Egeos.f90

### **Quick access**

```
Variables rhoz, orhoz
Routines getegeos(), initialize_egeos_mod(), getdvptr()
```

### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (strat(), radratio(), g1(), prmag(), g0(), ra(), pr(), ek(), g2(), polind()): Module containing the physical parameters

- horizontal\_data(dlh(), dphi(), phi()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_corrmov(), lverbose(), l\_anel()): Module containing the logicals that control the run
- radial\_functions(cheb\_norm(), i\_costf\_init(), d\_costf\_init(), r\_cmb(), r\_icb())
- blocking (1m2mc(), 1m2m(), 1m21()): Module containing blocking information
- fft\_jw (fft\_to\_real()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- cosine\_transform(costf1())
- plms\_theta(plm\_theta())
- truncation (n\_phi\_max(), lm\_max(), n\_r\_max(), l\_max(), minc(), nrpgeos(), n\_r\_maxgeos(), m\_max(), lm\_maxgeos(), n\_m\_max()): This module defines the grid points and the truncation
- communications (gather\_all\_from\_lo\_to\_rank0(), gt\_oc())
- parallel\_mod (rank ()): This module contains the blocking information
- output\_data(zdens(), tag(), nzmaxa(), runid(), nsmaxa(), sdens()): This module contains the parameters for output control
- chebint\_mod
- constants (ci(), two(), pi(), one(), half(), zero()): module containing constants and parameters used in the code.
- num\_param(tscale()): Module containing numerical and control parameters
- lmloop\_data(ulm(), llm())

### **Variables**

- egeos\_mod/rhoz (:,:) [real,private/allocatable]
- egeos\_mod/**dplms** (:,:,:) [real,private/allocatable]
- egeos\_mod/orhoz (:,:) [real,private/allocatable]
- egeos\_mod/osints(:,:) [real,private/allocatable]
- egeos\_mod/plms (:,:,:) [real,private/allocatable]
- egeos\_mod/i\_costf\_initz (:,:) [integer,private/allocatable]
- egeos\_mod/zz(:,:) [real,private/allocatable]
- egeos\_mod/nzmaxs (:) [integer,private/allocatable]
- egeos\_mod/rz(:,:) [real,private/allocatable]
- egeos\_mod/d\_costf\_initz(:,:) [real,private/allocatable]

### Subroutines and functions

```
subroutine egeos_mod/initialize_egeos_mod()
```

Called from magic

**subroutine** egeos\_mod/**getegeos** (time, ngeossets, w, dw, ddw, z, dz, egeos, ekntc, ekstc, ekin, dpflow, dzflow, cvzotc, cvorotc, chelotc)

Output of axisymmetric zonal flow, its relative strength, its time variation, and all forces acting on it. The slowest part in the TO process is the repitions calculation of Plms by subroutine plm\_theta. They are needed in getDVptr when I transform on the cylindrical grid. The necessary plms could simply be calculated one and then be stored for later use! See s outTOnew.f.

#### **Parameters**

- time [real,in]
- **ngeossets** [integer,in]
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dw** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*,*in*]
- **ddw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dz** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **egeos** [real,out]
- ekntc [real,out]
- **ekstc** [real,out]
- ekin [real,out]
- **dpflow** [real,out] :: RMS length scales
- **dzflow** [real,out]
- cvzotc [real,out]
- cvorotc [real,out]
- **chelotc** [real,out]

Called from outmisc()

```
Call to gather_all_from_lo_to_rank0(), chebintinit(), plm_theta(),
    getdvptr(), chebintd(), chebint()
```

**subroutine** egeos\_mod/**getdvptr** (ws, dws, ddws, zs, dzs, rmin, rmax, rs, nzmax, nzmaxa, plms, dplms, osints, lderiv, vrs, vts, vps, vors, dpek)

This subroutine calculates the three flow components VrS,VtS,VpS at a (r,theta,all phis) and (t,pi=theta, all phis). Here r=rS, PlmS=Plm(theta), dPlmS=sin(theta)\*dTheta Plm(theta), and OsinTS=1/sin(theta). The flow is calculated for all n\_phi\_max azimuthal points used in the code, and for corresponding latitudes north and south of the equator. For lDeriv=.true. the subroutine also calculates dpEk and dzEk which are phi averages of (d Vr/d phi)\*\*2 + (d Vtheta/d phi)\*\*2 + (d Vphi/d phi)\*\*2 and (d Vr/d z)\*\*2 + (d Vtheta/d z)\*\*2 + (d Vphi/d z)\*\*2, respectively. These two quantities are used to calculate z and phi scale of the flow in s\_getEgeos.f

**Note:** on input wS=w/r^2, dwS=dw/r, ddwS=ddw/r, zS=z/r

- ws (lm\_max,n\_r\_max) [complex,in]
- **dws** (*lm\_max*,*n\_r\_max*) [*complex*,*in*]

```
• ddws (lm_maxgeos,n_r_maxgeos) [complex,in]
```

- **zs** (lm\_maxgeos,n\_r\_maxgeos) [complex,in]
- **dzs** (lm\_maxgeos,n\_r\_maxgeos) [complex,in]
- rmin [real,in] :: radial bounds
- rmax [real,in]
- **rs** (*nzmaxa*) [real,in]
- nzmax [integer,in] :: number of (r,theta) points
- nzmaxa [integer,in,]
- **plms** (*lm\_maxgeos*,0.5 \* *nzmaxa* + 1.0) [*real,in*]
- **dplms**  $(lm\_maxgeos, 0.5 * nzmaxa + 1.0)$  [real,in]
- **osints** (0.5 \* *nzmaxa* + 1.0) [*real,in*]
- **Ideriv** [logical,in]
- vrs (nrpgeos,nzmaxa) [real,out]
- vts (nrpgeos,nzmaxa) [real,out]
- **vps** (nrpgeos,nzmaxa) [real,out]
- **vors** (nrpgeos,nzmaxa) [real,out]
- **dpek** (nzmaxa) [real,out]

```
Called from getegeos()
Call to fft_to_real()
```

### 10.17.11 outPV3.f90

### **Quick access**

```
Variables dplmz, vorold, plmz
Routines getpvptr(), outpv(), initialize_outpv3()
```

### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (radratio()): Module containing the physical parameters
- horizontal\_data(dlh(), dphi()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- logic(l\_sric(), lverbose()): Module containing the logicals that control the run
- radial\_functions(cheb\_norm(), i\_costf\_init(), d\_costf\_init(), r\_cmb(), r\_icb())
- blocking (1m2mc(), 1m2m(), 1m21(), 1m2()): Module containing blocking information
- fft\_jw (fft\_to\_real()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- cosine\_transform(costf1())

- plms\_theta(plm\_theta())
- truncation (n\_phi\_max(), lm\_max(), n\_r\_max(), minc(), m\_max(), l\_max(), n\_m\_max(), nrp()): This module defines the grid points and the truncation
- communications (gather\_all\_from\_lo\_to\_rank0(), gt\_oc())
- parallel mod (rank ()): This module contains the blocking information
- output\_data(nsmaxa(), sdens(), tag(), nzmaxa()): This module contains the parameters for output control
- to\_helpers (getpastr()): This module contains several helpful subroutines used in the TO calculations
- constants (ci(), two(), pi(), one(), half(), zero()): module containing constants and parameters used in the code.
- lmloop\_data(ulm(), llm())

### **Variables**

- outpv3/osints(:,:) [real,private/allocatable]
- outpv3/**dplmz** (:,:,:) [real,private/allocatable]
- outpv3/vorold(:,:,:) [real,private/allocatable]
- outpv3/plms (:,:,:) [real,private/allocatable]
- outpv3/plmz (:,:,:) [real,private/allocatable]
- outpv3/dplms (:,:,:) [real,private/allocatable]
- outpv3/rz(:,:) [real,private/allocatable]

### **Subroutines and functions**

```
subroutine outpv3/initialize_outpv3()
```

Called from magic

**subroutine** outpv3/outpv (time, l\_stop\_time, npvsets, w, dw, ddw, z, dz, omega\_ic, omega\_ma)

Output of z-integrated axisymmetric rotation rate Vp/s and s derivatives

- time [real,in]
- l\_stop\_time [logical,in]
- **npvsets** [integer,inout]
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **ddw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- dz (ulm-(llm)+1,n\_r\_max) [complex,in]
- omega\_ic [real,in]

• omega\_ma [real,in]

Called from output ()

**subroutine** outpv3/**getpvptr** (*w*, *dw*, *ddw*, *z*, *dz*, *rmin*, *rmax*, *rs*, *nzmax*, *nzmaxa*, *plms*, *dplms*, *osints*, *vrs*, *vps*, *vts*, *vors*, *dpvors*)

This subroutine calculates the three flow conponents VrS,VtS,VpS at (r,theta,all phis) and (r,pitheta, all phis). Here r=rS, PlmS=Plm(theta), dPlmS=sin(theta)\*dTheta Plm(theta), and OsinTS=1/sin(theta). The flow is calculated for all n\_phi\_max azimuthal points used in the code, and for corresponding latitudes north and south of the equator. For lDeriv=.true. the subroutine also calculates dpEk and dzEk which are phi averages of (d Vr/d phi)\*\*2 + (d Vtheta/d phi)\*\*2 + (d Vphi/d phi)\*\*2 and (d Vr/d z)\*\*2 + (d Vtheta/d z)\*\*2 + (d Vphi/d z)\*\*2, respectively. These two quantities are used ot calculate z and phi scale of the flow in s\_getEgeos.f NOTE: on input w=l\*(l+1)\*w

### **Parameters**

- w (lm\_max,n\_r\_max) [complex,in]
- **dw** (*lm\_max*,*n\_r\_max*) [complex,in]
- **ddw** (*lm\_max*,*n\_r\_max*) [*complex*,*in*]
- **z** (lm\_max,n\_r\_max) [complex,in]
- **dz** (*lm\_max*,*n\_r\_max*) [*complex*,*in*]
- **rmin** [real,in] :: radial bounds
- rmax [real,in]
- **rs** (nzmaxa) [real,in]
- nzmax [integer,in] :: number of (r,theta) points
- nzmaxa [integer,in,]
- plms  $(lm_max, 0.5 * nzmaxa + 1.0)$  [real, in]
- **dplms** (*lm\_max*,0.5 \* *nzmaxa* + 1.0) [*real,in*]
- **osints** (0.5 \* *nzmaxa* + 1.0) [*real,in*]
- vrs (nrp,nzmaxa) [real,out]
- **vps** (*nrp*,*nzmaxa*) [real,out]
- vts (nrp,nzmaxa) [real,out]
- **vors** (*nrp*,*nzmaxa*) [real,out]
- **dpvors** (nrp,nzmaxa) [real,out]

Called from outpv()

Call to fft\_to\_real()

### 10.17.12 chebInt.f90

### **Quick access**

```
Routines chebintd(), chebint(), chebintinit()
```

### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- chebyshev\_polynoms\_mod(cheb\_grid())
- radial\_der (get\_dcheb ()): Radial derivatives functions
- constants (half(), two(), four()): module containing constants and parameters used in the code.
- init\_costf(init\_costf1())
- cosine\_transform(costf1())

#### **Variables**

#### Subroutines and functions

#### **Parameters**

- **zmin** [real,in] :: integration interval!
- zmax [real,in]
- **znorm** [real,in] :: norm interval length
- nnorm [integer,in]:: suggested number of grid points for norm length
- ngridpointsmax [integer] :: dimension of z on input
- z (ngridpointsmax) [real,out] :: grid points, dimension at >= nGridPointsMax
- **ngridpoints** [integer,out] :: number of used grid points
- i\_costf\_init (2 \* ngridpointsmax + 2) [integer,out]
- **d\_costf\_init** (2 \* ngridpointsmax + 5) [real,out]

```
Called from outto(), getegeos()
```

```
Call to cheb_grid(), init_costf1()
```

**function** chebint\_mod/**chebint** (f, zmin, zmax, ngridpoints, ngridpointsmax, i\_costf\_init, d\_costf\_init)

- $\mathbf{f}$  (\*) [real,in] :: function on grid points
- **zmin** [real,in] :: integration boundaries
- **zmax** [real,in]
- **ngridpoints** [integer,in] :: No of grid points
- **ngridpointsmax** [integer,in,] :: No of max grid points

```
• i_costf_init (2 * ngridpointsmax + 2) [integer,in]
```

• **d\_costf\_init** (2 \* ngridpointsmax + 5) [real,in]

### Return chebint [real]

```
Called from outto(), getegeos()
```

**function** chebint\_mod/**chebintd**(f, lderiv, zmin, zmax, ngridpoints, ngridpointsmax,  $i\_costf\_init$ ,  $d\_costf\_init$ )

### **Parameters**

- **f** (\*) [real,inout] :: function on grid points
- **Ideriv** [logical,in]
- **zmin** [real,in] :: integration boundaries
- zmax [real,in]
- **ngridpoints** [integer,in] :: No of grid points
- ngridpointsmax [integer,in,] :: No of max grid points
- i\_costf\_init (2 \* ngridpointsmax + 2) [integer,in]
- **d\_costf\_init** (2 \* ngridpointsmax + 5) [real,in]

# Return chebintd [real]

Called from getegeos()

## 10.17.13 outOmega.f90

### **Description**

This module allows to compute the axisymmetric zonal flow versus the cylindrical radius s. By

### **Quick access**

```
Variables nsmax
Routines lnpas2tr(), outomega()
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- output\_data(tag()): This module contains the parameters for output control
- logic (lverbose ()): Module containing the logicals that control the run
- radial\_functions(i\_costf\_init(), d\_costf\_init(), r\_cmb(), r\_icb())
- blocking (1m2 ()): Module containing blocking information
- constants (one (), half (), two ()): module containing constants and parameters used in the code.
- cosine\_transform(costf1())
- plms\_theta(plm\_theta())

• truncation (lm\_max(), n\_r\_max(), l\_max(), minc()): This module defines the grid points and the truncation

### **Variables**

• omega/nsmax [integer,private/parameter=300] Number of cylindrical radial grid points

### Subroutines and functions

```
subroutine omega/outomega (z, omega_ic)
```

Output of axisymmetric zonal flow omega(s) into field omega. TAG, where s is the cylindrical radius. This is done for the southern and norther hemispheres at  $z=+-(r_icb+0.5)$ 

### **Parameters**

- **z** (lm\_max,n\_r\_max) [complex,in]
- omega\_ic [real,in]

```
Called from output ()
```

Call to Inpas2tr()

**function** omega/**lnpas2tr** (*f*, *lmmax*, *a*, *b*, *lmax*, *minc*, *nchebmax*, *theta*, *r*)

### **Parameters**

- **f** (lmmax,\*) [real,in]
- lmmax [integer,in,]
- **a** [real,in]
- **b** [real,in]
- lmax [integer,in]
- minc [integer,in]
- nchebmax [integer,in]
- theta [real,in]
- **r** [real,in]

### Return Inpas2tr [real]

```
Called from outomega()
```

Call to plm\_theta()

# 10.17.14 nl\_special\_calc.f90

### **Description**

This module allows to calculcate several diagnostics that need to be computed in the physical space (non-linear quantities)

### **Quick access**

Routines get\_helicity(), get\_perppar(), get\_nlblayers(), get\_fluxes()

### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (vischeatfac(), ek()): Module containing the physical parameters
- horizontal\_data (osn2(), o\_sin\_theta\_e2(), sn2(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- constants (one (), third(), half(), two(), pi()): module containing constants and parameters used in the code.
- radial\_functions(orho2(), or4(), temp0(), orho1(), or1(), visc(), or2(), beta())
- blocking (sizethetab(), nfs()): Module containing blocking information
- logic (l\_mag\_nl()): Module containing the logicals that control the run
- radial data(n r icb(), n r cmb())
- legendre\_grid\_to\_spec(legtfas2(), legtfas())
- truncation(n\_phi\_max(), 1\_maxmag(), 1\_max(), nrp()): This module defines the grid points and the truncation

#### **Variables**

### **Subroutines and functions**

Calculates axisymmetric contributions of:

- •the horizontal velocity  $u_h = \sqrt{u_\theta^2 + u_\phi^2}$
- •its radial derivative  $|\partial u_h/\partial r|$
- •The thermal dissipation rate  $(\nabla T)^2$

This subroutine is used when one wants to evaluate viscous and thermal dissipation layers

- **vt** (*nrp*,*nfs*) [real,in]
- **vp** (*nrp*,*nfs*) [*real*,*in*]
- **dvtdr** (nrp,nfs) [real,in]
- **dvpdr** (*nrp*,*nfs*) [real,in]
- **dsdr** (nrp,nfs) [real,in]
- **dsdt** (nrp,nfs) [real,in]
- **dsdp** (nrp,nfs) [real,in]

- **uhlmr** (*l\_max*+1) [*real,out*]
- **duhlmr** (*l max*+1) [real,out]
- gradslmr (l\_max+1) [real,out]
- **nr** [integer,in]
- nthetastart [integer,in]

Called from do\_iteration\_thetablocking\_seq(), do\_iteration\_thetablocking\_openmp()

Call to legtfas2(), legtfas()

Calculates the energies parallel and perpendicular to the rotation axis

•
$$E_{\perp} = 0.5(v_s^2 + v_{\phi}^2)$$
 with  $v_s = v_r \sin \theta + v_{\theta} \cos \theta$ 

•
$$E_{\parallel} = 0.5v_z^2$$
 with  $v_z = v_r \cos \theta - v_{\theta} * \sin \theta$ 

### **Parameters**

- **vr** (*nrp*,*nfs*) [real,in]
- **vt** (*nrp*,*nfs*) [*real*,*in*]
- **vp** (*nrp*,*nfs*) [real,in]
- **eperplmr** (*l\_max*+1) [real,out]
- eparlmr (l max+1) [real,out]
- **eperpaxilmr** (*l\_max*+1) [real,out]
- **eparaxilmr** (*l\_max*+1) [real,out]
- **nr** [integer,in]
- nthetastart [integer,in]

Called from do\_iteration\_thetablocking\_seq(), do\_iteration\_thetablocking\_openmp()

Call to legtfas2()

Calculates the fluxes:

- •Convective flux:  $F_c = \rho T(u_r s)$
- •Kinetic flux:  $F_k = 1/2 \, \rho u_r (u_r^2 + u_\theta^2 + u_\phi^2)$
- •Viscous flux:  $F_{=} (u \cdot S)_r$ )

If the run is magnetic, then this routine also computes:

- •Poynting flux
- •resistive flux

### **Parameters**

• **vr** (nrp,nfs) [real,in]

- **vt** (*nrp*,*nfs*) [real,in]
- **vp** (*nrp*,*nfs*) [*real*,*in*]
- **dvrdr** (nrp,nfs) [real,in]
- **dvtdr** (nrp,nfs) [real,in]
- **dvpdr** (*nrp*,*nfs*) [real,in]
- **dvrdt** (nrp,nfs) [real,in]
- **dvrdp** (*nrp*,*nfs*) [real,in]
- **sr** (*nrp*,*nfs*) [*real*,*in*]
- **pr** (nrp,nfs) [real,in]
- **br** (*nrp*,*nfs*) [real,in]
- **bt** (*nrp*,*nfs*) [real,in]
- **bp** (*nrp*,*nfs*) [real,in]
- **cbt** (nrp,nfs) [real,in]
- **cbp** (*nrp*,*nfs*) [*real*,*in*]
- **fconvlmr** (*l\_max*+1) [real,out]
- **fkinlmr** (*l\_max*+1) [real,out]
- **fvisclmr** (*l\_max*+1) [real,out]
- **fpoynlmr** (*l\_maxmag+1*) [real,out]
- **freslmr** (*l\_maxmag+1*) [real,out]
- **nr** [integer,in]
- **nthetastart** [integer,in]

Called from do\_iteration\_thetablocking\_seq(), do\_iteration\_thetablocking\_openmp()
Call to legtfas2(), legtfas()

Calculates axisymmetric contributions of helicity HelLMr and helicity\*\*2 Hel2LMr in (l,m=0,r) space.

- **vr** (*nrp*,*nfs*) [*real*,*in*]
- **vt** (*nrp*,*nfs*) [real,in]
- **vp** (*nrp*,*nfs*) [*real*,*in*]
- **cvr** (*nrp*,*nfs*) [real,in]
- **dvrdt** (*nrp*,*nfs*) [real,in]
- **dvrdp** (*nrp*,*nfs*) [real,in]
- **dvtdr** (nrp,nfs) [real,in]
- **dvpdr** (nrp,nfs) [real,in]

```
• hellmr (l_max+1) [real,out]
```

- **hel2lmr** (*l max*+1) [*real*, *out*]
- **helnalmr** (*l\_max*+1) [*real,out*]
- helna2lmr (*l\_max*+1) [real,out]
- **nr** [integer,in]
- **nthetastart** [integer,in]

```
Called from do_iteration_thetablocking_seq(), do_iteration_thetablocking_openmp()
Call to legtfas2()
```

# 10.18 Reading and storing check points (restart files)

### 10.18.1 readCheckPoints.f90

### **Description**

This module contains the functions that can help reading and mapping of the restart files

#### **Quick access**

### Needed modules

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters(kbotv(), radratio(), sigma\_ratio(), prmag(), ra(), pr(), ek(), ktopv()): Module containing the physical parameters
- init\_fields (omega\_ic2(), tipdipole(), scale\_b(), n\_start\_file(), tshift\_ic2(), scale\_s(), inform(), tomega\_ma1(), tomega\_ic1(), omegaosz\_ic1(), omega\_ma2(), start\_file(), scale\_v(), omegaosz\_ma1(), tomega\_ma2(), omegaosz\_ma2(), omega\_ma1(), tshift\_ma2(), omega\_ic1(), tshift\_ic1(), tshift\_ma1(), tomega\_ic2(), omegaosz\_ic2())
- logic (l\_rot\_ic(), l\_srma(), l\_cond\_ic(), l\_mag(), l\_sric(), l\_rot\_ma(), l\_mag\_lf(), l\_heat()): Module containing the logicals that control the run
- init\_costf(init\_costf1())
- radial\_functions (cheb\_norm(), cheb\_norm\_ic(), d\_costf\_init(), r(), i\_costf\_init(), d\_costfl\_ic\_init(), i\_costfl\_ic\_init())
- blocking (lm2(), lm2m(), lmstartb(), lm2l(), nlmbs(), lmstopb()): Module containing blocking information
- constants (two(), zero(), c\_z10\_omega\_ma(), c\_z10\_omega\_ic(), pi()): module containing constants and parameters used in the code.

- radial\_data(n\_r\_icb(), n\_r\_cmb())
- truncation (n\_r\_max(), m\_max(), n\_r\_ic\_maxmag(), lmagmem(), lm\_maxmag(), n\_phi\_tot(), lm\_max(), minc(), l\_max(), n\_r\_maxmag(), nalias(), n\_r\_ic\_max()): This module defines the grid points and the truncation
- cosine\_transform(costf1())

#### **Variables**

• readcheckpoints/bytes\_allocated[integer,private]

#### **Subroutines and functions**

read initial condition from restart file

- **w** (*lm\_max,n\_r\_max*) [*complex,out*]
- **dwdt** (*lm\_max*,*n\_r\_max*) [*complex*,*out*]
- **z** (lm\_max,n\_r\_max) [complex,out]
- **dzdt** (*lm max,n r max*) [complex,out]
- **p** (lm\_max,n\_r\_max) [complex,out]
- **dpdt** (*lm\_max,n\_r\_max*) [*complex,out*]
- **s** (*lm\_max,n\_r\_max*) [*complex,out*]
- **dsdt** (*lm\_max*,*n\_r\_max*) [*complex*,*out*]
- **b** (lm\_maxmag,n\_r\_maxmag) [complex,out]
- **dbdt** (*lm\_maxmag*,*n\_r\_maxmag*) [*complex*,*out*]
- **aj** (lm\_maxmag,n\_r\_maxmag) [complex,out]
- **djdt** (*lm\_maxmag*,*n\_r\_maxmag*) [*complex*,*out*]
- **b\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,out]
- **dbdt\_ic** (*lm\_maxmag*,*n\_r\_ic\_maxmag*) [*complex*,*out*]
- **aj\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,out]
- **djdt\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,out]
- omega\_ic [real,out]
- omega\_ma [real,out]
- lorentz\_torque\_ic [real,out]
- lorentz\_torque\_ma [real,out]
- time [real,out]

- **dt\_old** [real,out]
- **dt\_new** [real,out]
- n\_time\_step [integer,out]

Called from getstartfields()

Call to get1m21mo(), mapdatahydro(), mapdatamag()

### **Parameters**

- n\_r\_max [integer,in]
- n\_r\_max\_old [integer,in]
- l\_max [integer,in]
- l\_max\_old [integer,in]
- m\_max [integer,in]
- minc [integer,in]
- minc\_old [integer,in]
- inform [integer,in]
- lm\_max [integer,in]
- lm\_max\_old [integer,out]
- n\_data\_oldp [integer,out]
- lm2lmo (lm\_max) [integer,out]

Called from readstartfields()

- wo (n\_data\_oldp) [complex,in]
- **zo** (n\_data\_oldp) [complex,in]
- **po** (n\_data\_oldp) [complex,in]
- so (n\_data\_oldp) [complex,in]
- n\_data\_oldp [integer,in,]
- lm2lmo (lm\_max) [integer,in]
- n\_r\_max\_old [integer,in]
- lm\_max\_old [integer,in]
- n\_r\_maxl [integer,in]
- **lbc1** [logical,in]
- **lbc2** [logical,in]

```
• lbc3 [logical,in]
```

- **lbc4** [logical,in]
- w (lm\_max,n\_r\_max) [complex,out]
- **z** (lm\_max,n\_r\_max) [complex,out]
- **p** (lm\_max,n\_r\_max) [complex,out]
- **s** (*lm\_max*,*n\_r\_max*) [*complex*,*out*]

Called from readstartfields()

Call to mapdatar()

### **Parameters**

- wo (n\_data\_oldp) [complex,in]
- **zo** (n\_data\_oldp) [complex,in]
- **po** (n\_data\_oldp) [complex,in]
- so (n\_data\_oldp) [complex,in]
- n\_data\_oldp [integer,in,]
- n\_rad\_tot [integer,in]
- n\_r\_max\_old [integer,in]
- lm\_max\_old [integer,in]
- n\_r\_maxl [integer,in]
- lm2lmo (lm\_max) [integer,in]
- dim1 [integer,in]
- l\_ic [logical,in]
- w (lm\_maxmag,dim1) [complex,out]
- **z** (*lm\_maxmag*,dim1) [*complex*,out]
- **p** (*lm\_maxmag*,dim1) [*complex*,out]
- **s** (*lm\_maxmag*,dim1) [*complex,out*]

Called from readstartfields()

Call to mapdatar()

subroutine readcheckpoints/mapdatar (datar, n\_rad\_tot, n\_r\_max\_old, n\_r\_maxl, lbc, l\_ic)

Copy (interpolate) data (read from disc file) from old grid structure to new grid. Linear interploation is used in r if the radial grid structure differs

called in mapdata

- datar (\*) [complex,out]
- n\_rad\_tot [integer,in]
- n\_r\_max\_old [integer,in]

- n\_r\_maxl [integer,in]
- **lbc** [logical,in]
- l\_ic [logical,in]

```
Called from mapdatahydro(), mapdatamag()
```

Call to init\_costf1()

### 10.18.2 storeCheckPoints.f90

### **Description**

This module contains several subroutines that can be used to store the rst #.TAG files

#### **Quick access**

```
Routines store()
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- physical\_parameters (radratio(), sigma\_ratio(), prmag(), ra(), pr(), ek()): Module containing the physical parameters
- init\_fields (omega\_ic2(), omegaosz\_ma1(), tomega\_ma2(), omegaosz\_ma2(), omega\_ma1(), omega\_ic1(), tomega\_ic2(), inform(), omegaosz\_ic2(), tomega\_ma1(), tomega\_ic1(), omegaosz\_ic1(), omega\_ma2())
- output\_data(rst\_file(), n\_rst\_file()): This module contains the parameters for output control
- logic(l\_mag(), l\_heat(), l\_cond\_ic()): Module containing the logicals that control the run
- fieldslast (d\_omega\_ic\_dtlast(), lorentz\_torque\_malast(), d\_omega\_ma\_dtlast(), lorentz\_torque\_iclast()): This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- num\_param (tscale()): Module containing numerical and control parameters
- truncation (lm\_max(), n\_r\_max(), l\_max(), minc(), n\_theta\_max(), lm\_maxmag(), n\_r\_ic\_maxmag(), n\_phi\_tot(), n\_r\_maxmag(), nalias(), n\_r\_ic\_max()): This module defines the grid points and the truncation

#### **Variables**

### **Subroutines and functions**

```
subroutine storecheckpoints/store (time, dt, dtnew, w, z, p, s, b, aj, b_ic, aj_ic, dwdtlast, dzdtlast, dpdtlast, dsdtlast, dbdtlast, dbdt iclast, djdt iclast, djdt iclast)
```

store results on disc file (restart file) In addition to the magnetic field and velocity potentials we store the time derivative terms djdt(lm,nR),dbdt(lm,nR),.....

- time [real,in]
- **dt** [real,in]
- dtnew [real,in]
- w (lm\_max,n\_r\_max) [complex,in]
- **z** (lm\_max,n\_r\_max) [complex,in]
- **p** (lm\_max,n\_r\_max) [complex,in]
- **s** (lm\_max,n\_r\_max) [complex,in]
- **b** (lm\_maxmag,n\_r\_maxmag) [complex,in]
- aj (lm\_maxmag,n\_r\_maxmag) [complex,in]
- **b\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- aj\_ic (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **dwdtlast** (*lm\_max*,*n\_r\_max*) [*complex*,*in*]
- **dzdtlast** (*lm\_max*,*n\_r\_max*) [*complex*,*in*]
- **dpdtlast** (*lm\_max*,*n\_r\_max*) [*complex*,*in*]
- **dsdtlast** (*lm\_max*,*n\_r\_max*) [*complex*,*in*]
- **dbdtlast** (*lm\_maxmag*,*n\_r\_maxmag*) [*complex*,*in*]
- **djdtlast** (*lm\_maxmag*,*n\_r\_maxmag*) [*complex*,*in*]
- **dbdt\_iclast** (*lm\_maxmag*,*n\_r\_ic\_maxmag*) [*complex*,*in*]
- **djdt\_iclast** (*lm\_maxmag*,*n\_r\_ic\_maxmag*) [*complex*,*in*]

Called from output ()

# 10.19 Useful additional libraries

### 10.19.1 useful.f90

### **Description**

library with several useful subroutines

# **Quick access**

```
Routines random(), cc2real(), cc22real(), l_correct_step(), factorise(), safeopen(), safeclose(), logwrite()
```

### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- constants (one (), half (), two ()): module containing constants and parameters used in the code.
- output\_data (n\_log\_file(), log\_file()): This module contains the parameters for output control

- logic (l\_save\_out ()): Module containing the logicals that control the run
- parallel\_mod (rank ()): This module contains the blocking information

#### **Variables**

### Subroutines and functions

```
function useful/1_correct_step (n, t, t_last, n_max, n_step, n_intervals, n_ts, times, n_eo)
```

### **Parameters**

- **n** [integer,in] :: current step
- t [real,in] :: time at current step
- t last [real,in] :: last time at current step
- n max [integer,in] :: max number of steps
- **n\_step** [integer,in] :: action interval
- **n\_intervals** [integer,in] :: number of actions
- **n\_ts** [integer,in] :: number of times t
- **times** (\*) [real,in] :: times where l\_correct\_step == true
- **n\_eo** [integer,in] :: even/odd controller

### Return l\_correct\_step [logical]

```
Called from step_time()
```

function useful/random(r)

random number generator

```
if (r == 0) then random(r) = next random number (between 0. and 1.)
```

if (r < 0) then random(r) = previous random number

if (r > 0) then

random(r) = a new sequence of random numbers is started with seed r mod 1 note: r must be a non-integer to get a different seq

called in sinit

Parameters r [real,in]

**Return random** [real]

Called from inits(), initb(), initv()

subroutine useful/factorise (n, n\_facs, fac, n\_factors, factor)

Purpose of this subroutine is factorize n into a number of given factors fac(i).

- **n** [integer,in] :: number to be factorised!
- **n\_facs** [integer,in] :: number of facs to be tried!
- fac (\*) [integer,in] :: list of fators to be tried!

```
• n_factors [integer,out] :: number of factors used
              • factor (*) [integer, out] :: list of factors used
         Called from init_costf1(), init_fft(), init_costf2()
function useful/cc2real (c, m)
         Parameters
              • c [complex,in]
              • m [integer,in]
         Return cc2real [real]
         Called from getstartfields(), get_poltorrms(), get_power(), get_e_mag(),
             spectrum(), get_e_kin(), getdlm(), spectrum_temp_average(),
            hint2tor(), hint2dpol(), spectrum_temp(), rbpspec(), outpar(),
            spectrum_average(), hint2pol(), get_u_square(), rbrspec()
function useful/cc22real (c1, c2, m)
         Parameters
              • c1 [complex,in]
              • c2 [complex,in]
              • m [integer,in]
         Return cc22real [real]
         Called from get_power(), get_e_mag(), spectrum()
subroutine useful/safeopen (nf, file_name)
         Parameters
              • nf [integer,in]
              • file_name [character,in]
         Called from output(), step_time(), lmloop(), spectrum_temp_average(),
             spectrum average()
subroutine useful/safeclose (nf)
         Parameters of [integer,in]
         Called from output(), step_time(), lmloop(), spectrum_temp_average(),
             spectrum average()
subroutine useful/logwrite (message)
```

Called from outto(), initialize\_movie\_data(), dt\_courant(), output(),
 getstartfields(), initialize\_blocking(), step\_time(), precalc()

### 10.19.2 char\_manip.f90

# **Description**

This module contains several useful routines to manipule character strings

Parameters message [character,in]

#### **Quick access**

```
Routines length_to_char(), length_to_blank(), dble2str(), capitalize(), delete_string(), str2dble()
```

### **Needed modules**

• precision mod: This module controls the precision used in MagIC

### **Subroutines and functions**

```
subroutine charmanip/capitalize (string_bn)
```

Convert lower-case letters into capital letters

**Parameters string\_bn** [character,inout]

Called from step\_time(), get\_movie\_type(), readnamelists()

subroutine charmanip/delete\_string (string\_bn, string\_del, length)

Deletes string\_del from string and returns new length of string.

### **Parameters**

- **string\_bn** [character,inout]
- **string\_del** [character,in]
- **length** [integer,out]

Called from get\_movie\_type()

subroutine charmanip/str2dble(string\_bn, num)

interprets next word in string as an 1 real number deletes leading blanks and next\_word from string

#### **Parameters**

- string\_bn [character,in]
- **num** [real,out] :: output

Called from get\_movie\_type()

function charmanip/length\_to\_blank (string\_bn)

determines number of characters before first blank in string

**Parameters string\_bn** [character,in]

**Return length\_to\_blank** [integer]

```
Called from openfiles(), writenamelists(), get_movie_type(),
    readnamelists()
```

function charmanip/length\_to\_char (string\_bn, char\_bn)

- string\_bn [character,in]
- char\_bn [character,in]

Return length\_to\_char [integer]

subroutine charmanip/dble2str (num, str)

converts a 1 number num into a character str

#### **Parameters**

- num [real,in]
- **str** [character,out]

Called from outto(), output(), step\_time()

# 10.19.3 hdf5Helpers.f90

### **Description**

This module contains several useful tools to manipulate HDF5 files

### **Quick access**

```
Variables readhdf5_attribute, writehdf5_attribute
Routines write_dataset(), writehdf5_attr_dble(), readhdf5_attr_int(), writehdf5_attr_int()
```

### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- lmloop data(ulm(), llm())
- hdf5
- blocking (st\_map(), lo\_map()): Module containing blocking information

### Variables

- hdf5helpers/readhdf5\_attribute[public]
- hdf5helpers/writehdf5\_attribute[public]

### **Subroutines and functions**

subroutine hdf5helpers/write\_dataset (loc\_id, dataset\_name, dataset\_type, dat, dim1, dims\_full)

- loc\_id [integer,in]
- dataset\_name [character,in]

- dataset\_type [integer,in]
- dat (ulm-(llm)+1,dim1) [complex,in]
- dim1 [integer,in,]
- dims\_full (2) [integer,in]

subroutine hdf5helpers/readhdf5\_attr\_dble (loc\_id, attr\_name, attr\_value)

#### **Parameters**

- loc\_id [integer,in]
- attr\_name [character,in]
- attr\_value [real,out]

subroutine hdf5helpers/readhdf5\_attr\_int (loc\_id, attr\_name, attr\_value)

### **Parameters**

- loc\_id [integer,in]
- attr\_name [character,in]
- attr\_value [integer,out]

subroutine hdf5helpers/writehdf5\_attr\_dble(loc\_id, aspace\_id, attr\_name, attr\_value)

### **Parameters**

- loc\_id [integer,in]
- aspace\_id [integer,in]
- attr\_name [character,in]
- attr\_value [real,in]

subroutine hdf5helpers/writehdf5\_attr\_int (loc\_id, aspace\_id, attr\_name, attr\_value)

- loc\_id [integer,in]
- aspace\_id [integer,in]
- attr\_name [character,in]
- attr\_value [integer,in]

# FORTRAN MODULE INDEX

a	integration, 255
algebra, 246	k
b	kinetic_energy,267
bext, 164 blocking, 257  C charmanip, 351	leg_helper_mod, 231 legendre_grid_to_spec, 239 legendre_spec_to_grid, 235
chebint_mod, 338 chebyshev_polynoms_mod, 223 communications, 170 constants, 165	<pre>lmloop_data, 169 lmloop_mod, 196 lmmapping, 260 logic, 149</pre>
<pre>cosine_transform, 227 courant_mod, 192</pre>	m
d dtb_mod, 316	magnetic_energy, 268 matrices, 157 movie_data, 287
	n
e egeos_mod, 332	namelists, 174 nl_special_calc, 340
f fft_fac_mod, 229	nonlinear_bcs, 221 nonlinear_lm_mod, 219 num_param, 144
fft_jw, 241 fields, 152 fields_average_mod, 306	0
fieldslast, 155	omega, 339 out_coeff, 302
general_arrays_mod, 219	out_dtb_frame, 320 out_movie, 295 out_movie_ic, 301
getdlm_mod, 271 graphout_mod, 284 grenoble, 167	out_rms, 314 outmisc_mod, 272 outpar_mod, 276
h hdf5helpers,353 horizontal_data,187	output_data, 158 output_mod, 262 outpv3, 335 outrot, 273 outto_mod, 328
l	p
<pre>init_costf, 226 init_fields, 177</pre>	parallel_mod, 167

```
physical_parameters, 146
plms_theta, 230
power, 278
precalculations, 181
precision_mod, 140
radial_data, 168
radial_der, 248
radial_der_even, 252
radial_functions, 183
radial_spectra, 331
radialloop, 209
readcheckpoints, 344
riteration_mod, 211
riterthetablocking_mod, 213
riterthetablocking_openmp_mod, 215
rms, 308
rms_helpers, 311
S
spectra, 280
start_fields, 176
step_time_mod, 189
store_pot_mod, 305
storecheckpoints, 348
t
timing, 194
to_helpers, 327
torsional_oscillations, 323
truncation, 141
updateb_mod, 206
updates_mod, 203
updatewp_mod, 198
updatez_mod, 200
useful, 349
```

356 Fortran Module Index

## PYTHON MODULE INDEX

## m

magic.bLayers, 124
magic.coeff, 120
magic.cyl, 126
magic.libmagic, 131

358 Python Module Index

Symbols	aj (fortran variable in module fields), 154
add() (magic.Butterfly method), 130	aj_ave (fortran variable in module fields_average_mod),
add() (magic.Movie method), 118	308
init() (magic.AvgField method), 111	aj_ave_global (fortran variable in module
init() (magic.Butterfly method), 130	fields_average_mod), 307
init() (magic.CompSims method), 123	aj_ic (fortran variable in module fields), 154
init() (magic.MagicGraph method), 114	aj_ic_ave (fortran variable in module
init() (magic.MagicRSpec method), 121	fields_average_mod), 307
init() (magic.MagicRadial method), 112	aj_ic_lmloc (fortran variable in module fields), 154
init() (magic.MagicSetup method), 109	aj_lmloc (fortran variable in module fields), <b>154</b>
init() (magic.MagicSpectrum method), 112	aj_lmloc_container (fortran variable in module fields),
init() (magic.MagicSpectrum2D method), 113	154
init() (magic.MagicTs method), 110	aj_rloc (fortran variable in module fields), 154
init() (magic.Movie method), 118	aj_rloc_container (fortran variable in module fields), <b>154</b>
init() (magic.Movie3D method), 119	alffac (fortran variable in module num_param), 145
init() (magic.Surf method), 114	algebra (module), 246
init() (magic.TOMovie method), 122	allocate_common_arrays() (fortran subroutine in module
init() (magic.ThetaHeat method), 126	riterthetablocking_mod), 214
init() (magic.bLayers.BLayers method), 124	allocate_mappings() (fortran subroutine in module
init() (magic.coeff.MagicCoeffCmb method), 120	lmmapping), 261
init() (magic.coeff.MagicCoeffR method), 120	allocate_subblocks_mappings() (fortran subroutine in
init() (magic.cyl.Cyl method), 126	module lmmapping), 261
str() (magic.AvgField method), 111	alph1 (fortran variable in module radial_functions), 185
str() (magic.ThetaHeat method), 126	alph2 (fortran variable in module radial_functions), 184
str() (magic.bLayers.BLayers method), 124	alpha (fortran variable in module num_param), 144
weakref (magic.AvgField attribute), 111	alpha1 (fortran variable in module radial_functions), 185
weakref (magic.Butterfly attribute), 130	alpha2 (fortran variable in module radial_functions), 185
weakref (magic.CompSims attribute), 123	amp_b1 (fortran variable in module init_fields), 179
weakref (magic.MagicSetup attribute), 110	amp_curr (fortran variable in module bext), 165
weakref (magic.Movie attribute), 119	amp_imp (fortran variable in module bext), 165
weakref (magic.Movie3D attribute), 120	amp_s1 (fortran variable in module init_fields), 178
weakref (magic.Surf attribute), 115	amp_s2 (fortran variable in module init_fields), 179
weakref (magic.TOMovie attribute), 122	amp_v1 (fortran variable in module init_fields), 179
Λ.	amstart (fortran variable in module num_param), 144
A	anelprof() (in module magic.libmagic), 131
addtime() (fortran subroutine in module timing), 195	angular_file (fortran variable in module output_data), 159
advpol2hint (fortran variable in module rms), 310	arc2hint (fortran variable in module rms), 310
advpolas2hint (fortran variable in module rms), 309	arcas2hint (fortran variable in module rms), 310
advpollmr (fortran variable in module rms), 310	arclmr (fortran variable in module rms), 310
advtor2hint (fortran variable in module rms), 310	array_of_statuses (fortran variable in module communi-
advtoras2hint (fortran variable in module rms), 310	cations), 171
agrav (fortran variable in module radial_functions), 186	astrm (fortran variable in module outto_mod), 330

avg() (magic.cyl.Cyl method), 127 avg() (magic.Surf method), 115	bspdas (fortran variable in module torsional_oscillations), $324$
AvgField (class in magic), 111 avgField() (in module magic.libmagic), 131	bspdas_rloc (fortran variable in module torsional_oscillations), 324
avgStd() (magic.Movie method), 119 avgz() (magic.cyl.Cyl method), 127	bszas (fortran variable in module torsional_oscillations), $324$
В	bszas_rloc (fortran variable in module torsional_oscillations), <b>324</b>
b (fortran variable in module fields), 154	buo (fortran variable in module updatewp_mod), 199
b0 (fortran variable in module grenoble), 167	buo2hint (fortran variable in module rms), 309
b_ave (fortran variable in module fields_average_mod),	buoas2hint (fortran variable in module rms), 309
307	buofac (fortran variable in module physical_parameters),
b_ic (fortran variable in module fields), 155	148
b_ic_ave (fortran variable in module	buolmr (fortran variable in module rms), 309
fields_average_mod), 307	buomeanr (fortran variable in module power), 279
b_ic_lmloc (fortran variable in module fields), <b>153</b>	Butterfly (class in magic), 129
b_lmloc (fortran variable in module fields), <b>154</b>	bytes_allocated (fortran variable in module readcheck-
b_lmloc_container (fortran variable in module fields), 154	points), 345
b_r_file (fortran variable in module output_data), <b>161</b>	bzpdas (fortran variable in module torsional_oscillations),
b_rloc (fortran variable in module fields), 153	324
b_rloc_container (fortran variable in module fields), 154	bzpdas_rloc (fortran variable in module torsional_oscillations), 324
beta (fortran variable in module radial_functions), 184	sional_oscinations), 324
bext (module), 164	C
bic (fortran variable in module grenoble), 167	
BLayers (class in magic.bLayers), 124	c_dt_z10_ic (fortran variable in module constants), 166
blocking (module), 257  hmpt (fortren veriable in module matrices) 157	c_dt_z10_ma (fortran variable in module constants), 166
bmat (fortran variable in module matrices), 157 bmat_fac (fortran variable in module matrices), 157	c_lorentz_ic (fortran variable in module constants), 166
bmax_imp (fortran variable in module bext), 165	c_lorentz_ma (fortran variable in module constants), <b>166</b> c_moi_ic (fortran variable in module constants), <b>166</b>
bottcond (fortran variable in module radial_functions), 184	c_moi_ma (fortran variable in module constants), 165
bots (fortran variable in module init_fields), 178	c_moi_oc (fortran variable in module constants), 166
bpeakbot (fortran variable in module init_fields), 179	c_z10_omega_ic (fortran variable in module constants),
bpeaktop (fortran variable in module init_fields), 178	165
bpivot (fortran variable in module matrices), 158	c_z10_omega_ma (fortran variable in module constants),
bpsdas (fortran variable in module torsional_oscillations),	166
324	cacheblock_size_in_b (fortran variable in module block-
bpsdas_rloc (fortran variable in module tor-	ing), 258
sional_oscillations), 324 bpzas (fortran variable in module torsional_oscillations),	capitalize() (fortran subroutine in module charmanip), 352
324	cc22real() (fortran function in module useful), <b>351</b>
bpzas_rloc (fortran variable in module tor-	cc2real() (fortran function in module useful), 351
sional_oscillations), 324	cgesl() (fortran subroutine in module algebra), 246
bpzdas (fortran variable in module torsional_oscillations),	cgeslml() (fortran subroutine in module algebra), 246
324	charmanip (module), 351
bpzdas_rloc (fortran variable in module tor-	cheb (fortran variable in module radial_functions), 186
sional_oscillations), 324	cheb_grid() (fortran subroutine in module cheby-
bs2as (fortran variable in module torsional_oscillations),	shev_polynoms_mod), 225
324	cheb_ic (fortran variable in module radial_functions), 185
bs2as_rloc (fortran variable in module torsional_oscillations), 324	cheb_int (fortran variable in module radial_functions), 186
bspas (fortran variable in module torsional_oscillations),  324	cheb_int_ic (fortran variable in module radial_functions), 184
bspas_rloc (fortran variable in module torsional_oscillations), 324	cheb_norm (fortran variable in module radial_functions), 186

cheb_norm_ic (fortran variable in module ra- dial_functions), 184	<pre>costf1_complex_1d() (fortran subroutine in module co- sine_transform), 227</pre>
chebgrid() (in module magic.libmagic), 132	costf1_real() (fortran subroutine in module co-
chebint() (fortran function in module chebint_mod), 338	sine_transform), 228
chebint_mod (module), 338	costf1_real_1d() (fortran subroutine in module co-
chebintd() (fortran function in module chebint_mod), 339	sine_transform), 228
chebintinit() (fortran subroutine in module chebint_mod),	costf2() (fortran subroutine in module cosine_transform),
338	228
chebyshev_polynoms_mod (module), 223	costheta (fortran variable in module horizontal_data), 188
check_time_hits() (fortran subroutine in module step_time_mod), 192	courant() (fortran subroutine in module courant_mod), 193
checktruncation() (fortran subroutine in module trunca-	courant_mod (module), 192
tion), 143	courfac (fortran variable in module num_param), 145
chunksize (fortran variable in module parallel_mod), 168	cp (fortran variable in module precision_mod), 141
ci (fortran variable in module constants), 166	<pre>create_gather_type() (fortran subroutine in module com-</pre>
clm (fortran variable in module outto_mod), 329	munications), 172
closefiles() (fortran subroutine in module output_data), 164	create_lm2r_type() (fortran subroutine in module communications), 173
cmb_file (fortran variable in module output_data), 163	curlu2meanr (fortran variable in module power), 279
cmbhflux (fortran variable in module physi-	cut() (in module magic.libmagic), 132
cal_parameters), 147	Cyl (class in magic.cyl), 126
cmbmov_file (fortran variable in module output_data),	cylSder() (in module magic.libmagic), 132
162	cylZder() (in module magic.libmagic), 132
codeversion (fortran variable in module constants), 166	, , ,
communications (module), 170	D
CompSims (class in magic), 122	d2cheb (fortran variable in module radial_functions), 185
con_decrate (fortran variable in module physical_parameters), 148	d2cheb_ic (fortran variable in module radial_functions), 186
con_funcwidth (fortran variable in module physical_parameters), 147	d2temp0 (fortran variable in module radial_functions), 185
con_lambdamatch (fortran variable in module physical_parameters), 148	d3cheb (fortran variable in module radial_functions), 185 d_costf1_ic_init (fortran variable in module ra-
con_lambdaout (fortran variable in module physi-	dial_functions), 184
cal_parameters), 148	d_costf2_ic_init (fortran variable in module ra-
con_radratio (fortran variable in module physical_parameters), 149	dial_functions), 184
conductance_ma (fortran variable in module physi-	d_costf_init (fortran variable in module radial_functions),
cal_parameters), 146	184
constants (module), 165	d_costf_initc (fortran variable in module ra-
	dial_functions), 185
corfac (fortran variable in module physical_parameters),  147	d_costf_initz (fortran variable in module egeos_mod),  333
corm (fortran variable in module outto_mod), 329	d_costf_initz (fortran variable in module outto_mod), 330
corpol2hint (fortran variable in module rms), 309	d_fft_init (fortran variable in module fft_jw), 242
corpolas2hint (fortran variable in module rms), 309	d_l (fortran variable in module horizontal_data), 188
corpollmr (fortran variable in module rms), 310	d_lp1 (fortran variable in module horizontal_data), 188
cortor2hint (fortran variable in module rms), 310	d_m (fortran variable in module horizontal_data), 189
cortoras2hint (fortran variable in module rms), 309	d_mc2m (fortran variable in module horizontal_data), 189
cos36 (fortran variable in module constants), 166	d_omega_ic_dtlast (fortran variable in module fieldslast),
cos72 (fortran variable in module constants), <b>166</b>	156
cosine_transform (module), 227	d_omega_ma_dtlast (fortran variable in module field-
cosn2 (fortran variable in module horizontal_data), 188	slast), 156
costf1 (fortran variable in module cosine_transform), 227	db (fortran variable in module fields), 154
costf1_complex() (fortran subroutine in module co-	db0 (fortran variable in module grenoble), 167
sine_transform), 227	<del>-</del> · · ·

db_ave_global (fortran variable in module fields_average_mod), 308	difexp (fortran variable in module physical_parameters), 146
db_ic (fortran variable in module fields), 155	difkap (fortran variable in module num_param), 144
db_ic_lmloc (fortran variable in module fields), 155	difnu (fortran variable in module num_param), 145
db_lmloc (fortran variable in module fields), 155	difpol2hint (fortran variable in module rms), 310
db_rloc (fortran variable in module fields), 155	difpolas2hint (fortran variable in module rms), 319
dbd_iclast (fortran variable in module fieldslast), 156	difpollmr (fortran variable in module rms), 310
dbdt_iclast_lmloc (fortran variable in module fieldslast),	diftor2hint (fortran variable in module rms), 319
156	diftoras2hint (fortran variable in module rms), 309
dbdt_lmloc (fortran variable in module step_time_mod),  191	dipendipendipendipendipendipendipendipen
dbdt_rloc (fortran variable in module step_time_mod),	dipmean (fortran variable in module output_mod), 265
191	dipole_file (fortran variable in module output_data), 160
dbdtlast (fortran variable in module fieldslast), 156	dissnb (fortran variable in module physical_parameters),
dbdtlast_lmloc (fortran variable in module fieldslast), 156	146
dbeta (fortran variable in module radial_functions), 186	divktemp0 (fortran variable in module radial_functions),
dble2str() (fortran subroutine in module charmanip), 353	186
dcheb (fortran variable in module radial_functions), 185	dj (fortran variable in module fields), 154
dcheb_ic (fortran variable in module radial_functions),	dj_ic (fortran variable in module fields), 153
184	dj_ic_lmloc (fortran variable in module fields), 155
ddb (fortran variable in module fields), 154	dj_lmloc (fortran variable in module fields), 154
ddb0 (fortran variable in module grenoble), 167	dj_rloc (fortran variable in module fields), 154
ddb_ic (fortran variable in module fields), 154	djdt_iclast (fortran variable in module fieldslast), 156
ddb_ic_lmloc (fortran variable in module fields), 154	djdt_iclast_lmloc (fortran variable in module fieldslast),
ddb_lmloc (fortran variable in module fields), 155	156
ddb_rloc (fortran variable in module fields), 155	djdt_lmloc (fortran variable in module step_time_mod),
dddrx (fortran variable in module radial_functions), 184	191
ddj (fortran variable in module fields), 154	djdt_rloc (fortran variable in module step_time_mod),
ddj_ic (fortran variable in module fields), 154	191
ddj_ic_lmloc (fortran variable in module fields), 154	djdtlast (fortran variable in module fieldslast), 156
ddj_lmloc (fortran variable in module fields), 154	djdtlast_lmloc (fortran variable in module fieldslast), 156
ddrx (fortran variable in module radial_functions), 185	dlbmean (fortran variable in module output_mod), 264
ddw (fortran variable in module fields), 155	dlh (fortran variable in module horizontal_data), 188
ddw_lmloc (fortran variable in module fields), 154	dlkappa (fortran variable in module radial_functions), 185
ddw_rloc (fortran variable in module fields), 154	dllambda (fortran variable in module radial_functions),
ddzasl (fortran variable in module torsional_oscillations),	186
324	dlvcmean (fortran variable in module output_mod), 265
deallocate_common_arrays() (fortran subroutine in mod-	dlvcmeanr (fortran variable in module outpar_mod), 277
ule riterthetablocking_mod), 214	dlvisc (fortran variable in module radial_functions), 186
defaultnamelists() (fortran subroutine in module	dlymean (fortran variable in module output_mod), 264
namelists), 175	dlymeanr (fortran variable in module outpar_mod), 277
delete_string() (fortran subroutine in module charmanip), 352	dlvu2cmeanr (fortran variable in module outpar_mod), 277
delxh2 (fortran variable in module num_param), 145	dlvu2meanr (fortran variable in module outpar_mod), 277
delxr2 (fortran variable in module num_param), 145	dmbmean (fortran variable in module output_mod), 264
dentropy0 (fortran variable in module radial_functions), 186	dmvmean (fortran variable in module output_mod), <b>264</b> do_iteration_thetablocking_openmp() (fortran subroutine
deriv() (in module magic.coeff), 121	in module riterthetablocking_openmp_mod),
destroy_gather_type() (fortran subroutine in module com-	216
munications), 172	dp (fortran variable in module fields), 153
destroy_lm2r_type() (fortran subroutine in module com-	dp_lmloc (fortran variable in module fields), 154
munications), 173	dp_rloc (fortran variable in module fields), 155
dif (fortran variable in module updatewp_mod), 199	dpdt_lmloc (fortran variable in module step_time_mod),
difeta (fortran variable in module num param), 145	191

dpdt_rloc (fortran variable in module step_time_mod), 191	dtbrms_file (fortran variable in module output_data), 163 dtbtor2hint (fortran variable in module rms), 309
dpdtlast (fortran variable in module fieldslast), 156	dtbtoras2hint (fortran variable in module rms), 310
dpdtlast_lmloc (fortran variable in module fieldslast), <b>156</b>	dtdrms_file (fortran variable in module output_data), 161
dphi (fortran variable in module horizontal_data), 188	dteint (fortran variable in module output_mod), 264
dphi0 (fortran variable in module horizontal_data), 188	dtemp0 (fortran variable in module radial_functions), 186
dphi02 (fortran variable in module horizontal_data), 189	dtheta1a (fortran variable in module horizontal_data), 188
dpl0eq (fortran variable in module horizontal_data), 188	dtheta1s (fortran variable in module horizontal_data), 189
dplm (fortran variable in module horizontal_data), 189	dtheta2a (fortran variable in module horizontal_data), 188
dplms (fortran variable in module egeos_mod), 333	dtheta2s (fortran variable in module horizontal_data), 188
dplms (fortran variable in module outpv3), 336	dtheta3a (fortran variable in module horizontal_data), 188
dplms (fortran variable in module outto_mod), 330	dtheta3s (fortran variable in module horizontal_data), 188
dplmz (fortran variable in module outpv3), 336	dtheta4a (fortran variable in module horizontal_data), 188
dpymean (fortran variable in module output_mod), <b>265</b>	dtheta4s (fortran variable in module horizontal_data), 188
dr_fac (fortran variable in module radial_functions), 186	dtmax (fortran variable in module num_param), 144
dr_fac_ic (fortran variable in module radial_functions),	dtmin (fortran variable in module num_param), 145
186	dtstart (fortran variable in module num_param), 144
dr_facc (fortran variable in module radial_functions), <b>184</b>	dtvasrms_file (fortran variable in module output_data),
drx (fortran variable in module radial_functions), 185	163
ds (fortran variable in module fields), 153	dtvpol2hint (fortran variable in module rms), 309
ds_lmloc (fortran variable in module fields), <b>154</b>	dtypolas2hint (fortran variable in module rms), 310
ds_rloc (fortran variable in module fields), 153	dtypollmr (fortran variable in module rms), 310
dsdt_lmloc (fortran variable in module step_time_mod),	dtvrms() (fortran subroutine in module out_rms), 315
191	dtvrms_file (fortran variable in module output_data), 159
dsdt_rloc (fortran variable in module step_time_mod),	dtvtor2hint (fortran variable in module rms), 309
191	dtytoras2hint (fortran variable in module rms), 310
dsdtlast (fortran variable in module fieldslast), <b>156</b>	duhmeanr (fortran variable in module outpar_mod), 277
dsdtlast_lmloc (fortran variable in module fieldslast), <b>156</b>	dvpm (fortran variable in module outto_mod), 329
dt_bpot (fortran variable in module output_data), 161	dvsrlm_lmloc (fortran variable in module
dt_cmb (fortran variable in module output_data), 160	step_time_mod), 191
dt_cmb_file (fortran variable in module output_data), 160	dvsrlm_rloc (fortran variable in module step_time_mod),
dt_courant() (fortran subroutine in module courant_mod),	191
193	dvxbhlm_lmloc (fortran variable in module
dt_graph (fortran variable in module output_data), 163	step_time_mod), 191
dt_icb2_ave (fortran variable in module spectra), 282	dvxbhlm_rloc (fortran variable in module
dt_icb_ave (fortran variable in module spectra), 281	step_time_mod), 191
dt_log (fortran variable in module output_data), <b>161</b>	dw (fortran variable in module fields), <b>155</b>
dt_movie (fortran variable in module output_data), 163	dw_ave_global (fortran variable in module
dt_pot (fortran variable in module output_data), 160	fields_average_mod), 308
dt_r_field (fortran variable in module output_data), 160	dw_lmloc (fortran variable in module fields), 153
dt_rst (fortran variable in module output_data), 163	dw_rloc (fortran variable in module fields), 155
dt_spec (fortran variable in module output_data), 159	dwdt_lmloc (fortran variable in module step_time_mod),
dt_to (fortran variable in module output_data), 162	191
dt_tomovie (fortran variable in module output_data), <b>161</b>	dwdt_rloc (fortran variable in module step_time_mod),
dt_toz (fortran variable in module output_data), 163	191
dt_tpot (fortran variable in module output_data), <b>162</b>	dwdtlast (fortran variable in module fieldslast), <b>156</b>
dt_vpot (fortran variable in module output_data), 163	dwdtlast_lmloc (fortran variable in module fieldslast), 156
dtb_gather_rloc_on_rank0() (fortran subroutine in mod-	dz (fortran variable in module fields), 153
ule dtb_mod), 318	dz_lmloc (fortran variable in module fields), 155
dtb_mod (module), 316	dz_rloc (fortran variable in module fields), 153
dtbpol2hint (fortran variable in module rms), 310	dzastrlmr (fortran variable in module tor-
dtbpolas2hint (fortran variable in module rms), 309	sional_oscillations), 324
dtbpollmr (fortran variable in module rms), 310	dzastrlmr_rloc (fortran variable in module tor-
dtbrms() (fortran subroutine in module out_rms), 316	sional_oscillations), 324

dzcorlmr (fortran variable in module torsional_oscillations), 324	e_p_asa (fortran variable in module magnetic_energy), $269$
dzcorlmr_rloc (fortran variable in module torsional_oscillations), 324	e_p_l_ave (fortran variable in module spectra), <b>282</b> e_p_m_ave (fortran variable in module spectra), <b>281</b>
dzddvplmr (fortran variable in module tor-	e_pa (fortran variable in module kinetic_energy), 267
sional_oscillations), 324	e_pa (fortran variable in module magnetic_energy), 269
dzddvplmr_rloc (fortran variable in module tor-	e_t2_l_ave (fortran variable in module spectra), 282
sional_oscillations), 324	e_t2_m_ave (fortran variable in module spectra), 282
dzdt_lmloc (fortran variable in module step_time_mod),	e_t_asa (fortran variable in module kinetic_energy), 267
191	e_t_asa (fortran variable in module magnetic_energy),
dzdt_rloc (fortran variable in module step_time_mod),	269
dzdtlast (fortran variable in module fieldslast), <b>156</b>	e_t_l_ave (fortran variable in module spectra), 281 e_t_m_ave (fortran variable in module spectra), 282
dzdtlast_lo (fortran variable in module fieldslast), 156	e_ta (fortran variable in module kinetic_energy), 267
dzdvplmr (fortran variable in module tor-	e_ta (fortran variable in module magnetic_energy), 269
sional_oscillations), 324	egeos_mod (module), 332
dzdvplmr_rloc (fortran variable in module tor-	ek (fortran variable in module physical_parameters), 147
sional_oscillations), 324	ek_p2_l_ave (fortran variable in module spectra), <b>282</b>
dzlflmr (fortran variable in module tor-	ek_p2_m_ave (fortran variable in module spectra), 282
sional_oscillations), 324	ek_p_l_ave (fortran variable in module spectra), 281
dzlflmr_rloc (fortran variable in module tor-	ek_p_m_ave (fortran variable in module spectra), 282
sional_oscillations), 324	ek_t2_l_ave (fortran variable in module spectra), 282
dzrstrlmr (fortran variable in module tor-	ek_t2_m_ave (fortran variable in module spectra), <b>282</b>
sional_oscillations), 324	ek_t_l_ave (fortran variable in module spectra), 282
dzrstrlmr_rloc (fortran variable in module tor-	ek_t_m_ave (fortran variable in module spectra), 282
sional_oscillations), 324	ekscaled (fortran variable in module physi-
dzstrlmr (fortran variable in module torsional_oscillations), 324	cal_parameters), 147
dzstrlmr_rloc (fortran variable in module tor-	elcmbmean (fortran variable in module output_mod), 264 elmean (fortran variable in module output_mod), 264
sional_oscillations), 324	enscale (fortran variable in module num_param), 145
dzvmean (fortran variable in module output_mod), 264	eparaximeanr (fortran variable in module outpar_mod),
az mean (fortain variable in module output_mod), 201	277
E	eparmeanr (fortran variable in module outpar_mod), 277
e_cmb2_l_ave (fortran variable in module spectra), <b>282</b>	eperpaximeanr (fortran variable in module outpar_mod),
e_cmb2_m_ave (fortran variable in module spectra), 281	277
e_cmb_l_ave (fortran variable in module spectra), 282	eperpmeanr (fortran variable in module outpar_mod), 277
e_cmb_m_ave (fortran variable in module spectra), 282	epsc (fortran variable in module physical_parameters),
e_dipa (fortran variable in module magnetic_energy), 269	147
e_kin_file (fortran variable in module output_data), 162	epsc0 (fortran variable in module physical_parameters),
e_kin_pmean (fortran variable in module output_mod),	147
264	epscprof (fortran variable in module radial_functions),
e_kin_tmean (fortran variable in module output_mod),	185
265	epss (fortran variable in module physical_parameters), 146
e_mag_ic_file (fortran variable in module output_data),	equat() (magic.cyl.Cyl method), 127
159	equat() (magic.Surf method), 115
e_mag_oc_file (fortran variable in module output_data),  162	escale (fortran variable in module num_param), 145
e_mag_pmean (fortran variable in module output_mod),	etot (fortran variable in module output_mod), <b>264</b>
264	etotold (fortran variable in module output_mod), 265
e_mag_tmean (fortran variable in module output_mod),	expo_imp (fortran variable in module bext), 165
264	
e_p2_l_ave (fortran variable in module spectra), <b>282</b>	F
e_p2_m_ave (fortran variable in module spectra), 282	fac_loop (fortran variable in module bext), 165
e_p_asa (fortran variable in module kinetic_energy), 267	factorise() (fortran subroutine in module useful), 350

fast_read() (in module magic.libmagic), 133	geolmr (fortran variable in module rms), 310
fcondmeanr (fortran variable in module outpar_mod), 277	geosmean (fortran variable in module output_mod), 264
fconvmeanr (fortran variable in module outpar_mod), 277	get_angular_moment() (fortran subroutine in module out-
fft99ajw() (fortran subroutine in module fft_jw), 244	rot), 275
fft99bjw() (fortran subroutine in module fft_jw), 244	get_b_nl_bcs() (fortran subroutine in module nonlin-
fft_fac_complex() (fortran subroutine in module	ear_bcs), <b>222</b>
fft_fac_mod), 229	get_b_surface() (fortran subroutine in module
fft_fac_mod (module), 229	out_movie), <b>301</b>
fft_fac_real() (fortran subroutine in module fft_fac_mod),	<pre>get_bmat() (fortran subroutine in module updateb_mod),</pre>
229	208
fft_jw (module), 241	<pre>get_bpol() (fortran subroutine in module out_dtb_frame),</pre>
fft_thetab() (fortran subroutine in module fft_jw), 242	321
fft_to_real() (fortran subroutine in module fft_jw), 242	get_br_v_bcs() (fortran subroutine in module nonlin-
fftjw() (fortran subroutine in module fft_jw), 242	ear_bcs), 222
fields (module), 152	get_btor() (fortran subroutine in module out_dtb_frame),
fields_average() (fortran subroutine in module	322
fields_average_mod), 308	get_chebs (fortran variable in module cheby-
fields_average_mod (module), 306	shev_polynoms_mod), 223
fieldslast (module), 155	get_chebs_direct() (fortran subroutine in module cheby-
	· ·
final_wait_array (fortran variable in module communica-	shev_polynoms_mod), 224
tions), 171	get_chebs_even() (fortran subroutine in module cheby-
finalize() (fortran subroutine in module nonlin-	shev_polynoms_mod), 224
ear_lm_mod), 220	get_chebs_recurr() (fortran subroutine in module cheby-
finalize_movie_data() (fortran subroutine in module	shev_polynoms_mod), 224
movie_data), 289	get_dcheb (fortran variable in module radial_der), 248
finalize_radialloop() (fortran subroutine in module radialloop), <b>209</b>	<pre>get_dcheb_complex() (fortran subroutine in module ra- dial_der), 251</pre>
finalize_riterthetablocking_openmp() (fortran subroutine	get_dcheb_even() (fortran subroutine in module ra-
in module riterthetablocking_openmp_mod),	dial_der_even), 255
216	get_dcheb_real_1d() (fortran subroutine in module ra-
finalize_updatewp() (fortran subroutine in module up-	dial_der), <b>251</b>
datewp_mod), <b>199</b>	<pre>get_ddcheb() (fortran subroutine in module radial_der),</pre>
fkinmeanr (fortran variable in module outpar_mod), 277	251
four (fortran variable in module constants), 166	get_ddcheb_even() (fortran subroutine in module ra-
fourier2D() (magic.Butterfly method), 130	dial_der_even), 255
fpoynmeanr (fortran variable in module outpar_mod), 277	<pre>get_dddcheb() (fortran subroutine in module radial_der),</pre>
frames (fortran variable in module movie_data), 288	252
fresmeanr (fortran variable in module outpar mod), 277	get_dddr() (fortran subroutine in module radial_der), 250
fviscmeanr (fortran variable in module outpar_mod), 277	get_ddr() (fortran subroutine in module radial_der), 249
1 - //	get_ddr_even() (fortran subroutine in module ra-
G	dial_der_even), 253
	get_ddrns_even() (fortran subroutine in module ra-
g0 (fortran variable in module physical_parameters), 147	dial_der_even), 254
g1 (fortran variable in module physical_parameters), 148 g2 (fortran variable in module physical_parameters), 147	get_dh_dtblm() (fortran subroutine in module dtb_mod),
	319
gather_all_from_lo_to_rank0() (fortran subroutine in	get_dr (fortran variable in module radial_der), 248
module communications), 172	get_dr_complex() (fortran subroutine in module ra-
gather_from_lo_to_rank0() (fortran subroutine in module communications), 172	dial_der), 248
gauleg() (fortran subroutine in module horizontal_data), 189	get_dr_real_1d() (fortran subroutine in module ra- dial_der), 249
gauss (fortran variable in module horizontal_data), 188	get_drns() (fortran subroutine in module radial_der), 249
general_arrays_mod (module), 219	get_drns_even() (fortran subroutine in module ra-
geo2hint (fortran variable in module rms), 309	dial_der_even), 253
geoas2hint (fortran variable in module rms), 310	<pre>get_dtb() (fortran subroutine in module out_dtb_frame),</pre>
O	

321 get dtblm() (fortran subroutine in module dtb mod), 318 get dtblmfinish() (fortran subroutine in module dtb\_mod), 319 ki-(fortran subroutine get\_e\_kin() module netic energy), 267 get e mag() (fortran subroutine in module magnetic energy), 270 get\_fl() (fortran subroutine in module out\_movie), 301 subroutine get\_fluxes() (fortran module nl\_special\_calc), 342 get\_global\_sum (fortran variable in module communications), 171 get\_global\_sum\_cmplx\_1d() (fortran function in module communications), 172 get\_global\_sum\_cmplx\_2d() (fortran function in module communications), 172 get\_global\_sum\_real\_2d() (fortran function in module communications), 172 get\_helicity() (fortran subroutine in module nl\_special\_calc), 343 get\_hit\_times() (fortran subroutine in module precalculations), 182 get\_lorder\_lm\_blocking() (fortran subroutine in module blocking), 259 get\_lorentz\_torque() (fortran subroutine in module outrot), 275 get\_movie\_type() (fortran subroutine module movie\_data), 289 (fortran subroutine get\_nlblayers() in module nl\_special\_calc), 341 get\_pas() (fortran subroutine in module to\_helpers), 328 get\_paslm() (fortran subroutine in module rms\_helpers), 311 get\_perppar() (fortran subroutine in module nl special calc), 342 get poltorrms() (fortran subroutine in module rms\_helpers), 312 get power() (fortran subroutine in module power), 279 get\_ras() (fortran subroutine in module rms\_helpers), 313 get s0mat() (fortran subroutine in module updates mod), 205 get sl() (fortran subroutine in module out movie), 300 get\_smat() (fortran subroutine in module updates\_mod), get\_snake\_lm\_blocking() (fortran subroutine in module blocking), 259 get\_standard\_deviation() (fortran function in module spectra), 282 get\_standard\_lm\_blocking() (fortran subroutine in module blocking), 259 get\_subblocks() (fortran subroutine in module blocking), 259

(fortran subroutine in module nonlin-

ear lm mod), 220 get theta blocking (fortran variable in module blocking), get\_theta\_blocking\_cache() (fortran subroutine in module blocking), 259 get theta blocking openmp() (fortran subroutine in module blocking), 260 get\_u\_square() (fortran subroutine in module kinetic energy), 268 get\_viscous\_torque (fortran variable in module outrot), get\_viscous\_torque\_complex() (fortran subroutine in module outrot), 275 get\_viscous\_torque\_real() (fortran subroutine in module outrot), 274 get\_wpmat() (fortran subroutine in module datewp\_mod), 200 get z10mat() (fortran subroutine in module datez mod), 202 get zmat() (fortran subroutine in module updatez mod), getAccuratePeaks() (in module magic.bLayers), 124 getastr() (fortran subroutine in module to\_helpers), 328 getbackground() (fortran subroutine in module radial functions), 186 getCpuTime() (in module magic.libmagic), 133 getdlm() (fortran subroutine in module getdlm\_mod), 271 getdlm\_mod (module), 271 getdvptr() (fortran subroutine in module egeos\_mod), 334 getegeos() (fortran subroutine in module egeos mod), 333 getGauss() (in module magic.coeff), 121 getlm2lmo() (fortran subroutine in module readcheckpoints), 346 getMaxima() (in module magic.bLayers), 125 getpastr() (fortran subroutine in module to helpers), 327 getpvptr() (fortran subroutine in module outpv3), 337 getstartfields() (fortran subroutine in module start fields), getthistype() (fortran function in module riterthetablocking\_openmp\_mod), 216 (fortran subroutine in module getto() torsional oscillations), 325 (fortran subroutine in module gettofinish() torsional\_oscillations), 326 (fortran subroutine in gettonext() module sional\_oscillations), 326 getTotalRunTime() (in module magic.libmagic), 133 gradt2meanr (fortran variable in module outpar\_mod), graph\_file (fortran variable in module output\_data), 163 graph\_mpi\_fh (fortran variable in module output data),

366 Index

162

(fortran

graphout mod), 286

subroutine

in

module

graph\_write()

graph write mpi() (fortran subroutine in module init costf1() (fortran subroutine in module init costf), graphout mod), 287 graphout() (fortran subroutine in module graphout mod), graphout\_ic() (fortran subroutine in module graphout mod), 286 graphout mod (module), 284 graphout mpi() (fortran subroutine module graphout mod), 285 graphout\_mpi\_header() (fortran subroutine in module graphout\_mod), 286 grenoble (module), 167 gt cheb (fortran variable in module communications), 171 gt\_ic (fortran variable in module communications), 171 gt\_oc (fortran variable in module communications), 171 Η half (fortran variable in module constants), 165 hammer2cart() (in module magic.libmagic), 133 hdf5helpers (module), 353 hdif b (fortran variable in module horizontal data), 189 hdif s (fortran variable in module horizontal data), 188 hdif v (fortran variable in module horizontal data), 188 hint2dpol() (fortran subroutine in module rms helpers), 312 hint2pol() (fortran subroutine in module rms\_helpers), 312 hint2tor() (fortran subroutine in module rms\_helpers), horizontal() (fortran subroutine in module horizontal data), 189 horizontal\_data (module), 187 i\_costf1\_ic\_init (fortran variable in module dial functions), 185 i\_costf2\_ic\_init (fortran variable in module dial\_functions), 186 i\_costf\_init (fortran variable in module radial\_functions), 186 i\_costf\_initc (fortran variable in module dial functions), 185 i costf initz (fortran variable in module egeos mod), 333 i\_costf\_initz (fortran variable in module outto\_mod), 330 i fft init (fortran variable in module fft jw), 242 ierr (fortran variable in module parallel\_mod), 168 imagcon (fortran variable in module physical parameters), 148 imps (fortran variable in module physical parameters), inform (fortran variable in module init\_fields), 179 init\_b1 (fortran variable in module init\_fields), 178

init\_costf (module), 226

- init costf2() (fortran subroutine in module init costf),
- init fft() (fortran subroutine in module fft jw), 242 init fields (module), 177
- init rnb() (fortran subroutine in module rms helpers). 313
- init s1 (fortran variable in module init fields), 179
- init\_s2 (fortran variable in module init\_fields), 178
- init\_v1 (fortran variable in module init\_fields), 178
- initb() (fortran subroutine in module init\_fields), 180
- initialize() (fortran subroutine in module leg\_helper\_mod), 232
- initialize() (fortran subroutine in module nonlinear\_lm\_mod), 220
- initialize\_blocking() (fortran subroutine in module blocking), 259
- initialize communications() (fortran subroutine in module communications), 171
- initialize dtb mod() (fortran subroutine in module dtb mod), 318
- initialize\_egeos\_mod() (fortran subroutine in module egeos\_mod), 333
- initialize fields() (fortran subroutine in module fields),
- initialize\_fields\_average\_mod() (fortran subroutine in module fields\_average\_mod), 308
- initialize\_fieldslast() (fortran subroutine in module fieldslast), 156
- initialize\_grenoble() (fortran subroutine in module grenoble), 167
- initialize\_horizontal\_data() (fortran subroutine in module horizontal\_data), 189
- initialize init fields() (fortran subroutine in module init fields), 179
- initialize kinetic energy() (fortran subroutine in module kinetic\_energy), 267
- initialize lmloop() (fortran subroutine in module lmloop\_mod), 197
- initialize Imloop data() (fortran subroutine in module Imloop data), 169
- initialize magnetic energy() (fortran subroutine in module magnetic\_energy), 269
- initialize\_matrices() (fortran subroutine in module matrices), 158
- initialize\_movie\_data() (fortran subroutine in module movie\_data), 288
- initialize\_num\_param() (fortran subroutine in module num\_param), 145
- initialize\_outpar\_mod() (fortran subroutine in module outpar mod), 277
- initialize output() (fortran subroutine in module output mod), 265

initialize_output_power() (fortran subroutine in module power), 279	kbots (fortran variable in module physical_parameters), 148
initialize_outpv3() (fortran subroutine in module outpv3), 336	kbotv (fortran variable in module physical_parameters), 147
initialize_outto_mod() (fortran subroutine in module outto_mod), 330	kinetic_energy (module), 267 ktopb (fortran variable in module physical_parameters),
initialize_radial_data() (fortran subroutine in module radial_data), 169	148 ktops (fortran variable in module physical_parameters),
initialize_radial_functions() (fortran subroutine in module radial_functions), 186	148 ktopy (fortran variable in module physical_parameters),
initialize_radialloop() (fortran subroutine in module radialloop), <b>209</b>	147
initialize_riterthetablocking_openmp() (fortran subroutine in module riterthetablocking_openmp_mod), 216	L 12lmas (fortran variable in module blocking), 258 1_am (fortran variable in module logic), 149
initialize_rms() (fortran subroutine in module rms), 310	l_anel (fortran variable in module logic), <b>151</b>
initialize_spectra() (fortran subroutine in module spectra), 282	l_anelastic_liquid (fortran variable in module logic), 151 l_average (fortran variable in module logic), 150
initialize_step_time() (fortran subroutine in module step_time_mod), 191	l_b_nl_cmb (fortran variable in module logic), 152 l_b_nl_icb (fortran variable in module logic), 150
initialize_to() (fortran subroutine in module tor- sional_oscillations), 325	l_cmb_field (fortran variable in module logic), 152 l_cond_ic (fortran variable in module logic), 150
initialize_truncation() (fortran subroutine in module truncation), 143	l_cond_ma (fortran variable in module logic), <b>150</b> l_conv (fortran variable in module logic), <b>151</b>
initialize_updateb() (fortran subroutine in module updateb_mod), 207	l_conv_nl (fortran variable in module logic), 150 l_corr (fortran variable in module logic), 150
initialize_updates() (fortran subroutine in module updates_mod), 204	l_correct_ame (fortran variable in module logic), <b>151</b> l_correct_amz (fortran variable in module logic), <b>151</b>
initialize_updatewp() (fortran subroutine in module updatewp_mod), 199	l_correct_step() (fortran function in module useful), <b>350</b> l_corrmov (fortran variable in module logic), <b>150</b>
initialize_updatez() (fortran subroutine in module updatez_mod), 202	l_curr (fortran variable in module bext), <b>165</b> l_drift (fortran variable in module logic), <b>152</b>
inits() (fortran subroutine in module init_fields), 180	l_dt_cmb_field (fortran variable in module logic), <b>151</b>
initv() (fortran subroutine in module init_fields), 179	l_dtb (fortran variable in module logic), 149
intcheb() (in module magic.libmagic), 134	l_dtbmovie (fortran variable in module logic), 151
integBotTop() (in module magic.bLayers), 125	l_dtrmagspec (fortran variable in module logic), 152
integBulkBc() (in module magic.bLayers), 125	l_fluxprofs (fortran variable in module logic), 149
integration (module), 255	l_graph_time (fortran variable in module output_data),
interior_model (fortran variable in module physi-	161
cal_parameters), 147	l_heat (fortran variable in module logic), 152
intfac (fortran variable in module num_param), 144 istop (fortran variable in module num_param), 145	l_heat_nl (fortran variable in module logic), 152 l_hel (fortran variable in module logic), 152
J	l_ht (fortran variable in module logic), 151 l_htmovie (fortran variable in module logic), 152
j_cond() (fortran subroutine in module init_fields), 180	l_imp (fortran variable in module bext), 165
jmat (fortran variable in module matrices), 157	l_iner (fortran variable in module logic), 152
jmat_fac (fortran variable in module matrices), 158	l_isothermal (fortran variable in module logic), <b>151</b>
jpivot (fortran variable in module matrices), 157	l_lcr (fortran variable in module logic), <b>152</b>
jvarcon (fortran variable in module radial_functions), 184	l_mag (fortran variable in module logic), 152
V	l_mag_kin (fortran variable in module logic), 150
K	l_mag_lf (fortran variable in module logic), 151
kappa (fortran variable in module radial_functions), 186	l_mag_nl (fortran variable in module logic), 150
kbotb (fortran variable in module physical_parameters),	l_max (fortran variable in module truncation), 142 l_max_cmb (fortran variable in module output_data), 161
1/7	1_max_cmo (tornam variable in module output data), 101

l_max_r (fortran variable in module output_data), 160	legtf() (fortran subroutine in module legen-
l_maxmag (fortran variable in module truncation), 142	dre_spec_to_grid), 237
l_movie (fortran variable in module logic), 152	legtf1() (fortran subroutine in module legen-
l_movie_ic (fortran variable in module logic), 152	dre_grid_to_spec), 239
l_movie_oc (fortran variable in module logic), 151	legtf2() (fortran subroutine in module legen-
l_newmap (fortran variable in module logic), 150	dre_grid_to_spec), 240
l_non_rot (fortran variable in module logic), 151	legtf3() (fortran subroutine in module legen-
l_par (fortran variable in module logic), 152	dre_grid_to_spec), 240
l_perppar (fortran variable in module logic), 150	legtfas() (fortran subroutine in module legen-
l_power (fortran variable in module logic), 149	dre_grid_to_spec), 240
l_pv (fortran variable in module logic), 151	legtfas2() (fortran subroutine in module legen-
l_r_field (fortran variable in module logic), 150	dre_grid_to_spec), 240
l_r_fieldt (fortran variable in module logic), 150	legtfg() (fortran subroutine in module legen-
l_reset_t (fortran variable in module init_fields), 178	dre_spec_to_grid), 235
l_rmagspec (fortran variable in module logic), 149	legtfgnomag() (fortran subroutine in module legen-
l_rms (fortran variable in module logic), 152	dre_spec_to_grid), 237
l_rmstest (fortran variable in module logic), 151	length_to_blank() (fortran function in module charma-
l_rot_ic (fortran variable in module logic), 150	nip), 352
l_rot_ma (fortran variable in module logic), 150	length_to_char() (fortran function in module charmanip),
l_runtimelimit (fortran variable in module logic), 151	352
l_save_out (fortran variable in module logic), 152	lffac (fortran variable in module physical_parameters),
l_sric (fortran variable in module logic), 150	149
l_srma (fortran variable in module logic), 149	lfm (fortran variable in module outto_mod), 330
l_start_file (fortran variable in module init_fields), 179	lfpol2hint (fortran variable in module rms), 310
l_store_frame (fortran variable in module logic), 152	lfpolas2hint (fortran variable in module rms), 310
_storebpot (fortran variable in module logic), 152	lfpollmr (fortran variable in module rms), 310
l_storepot (fortran variable in module logic), 151	lftor2hint (fortran variable in module rms), 309
l_storetpot (fortran variable in module logic), 149	lftoras2hint (fortran variable in module rms), 309
_storevpot (fortran variable in module logic), 150	lgeos (fortran variable in module truncation), 141
l_time_hits (fortran variable in module logic), 151	lgrenoble (fortran variable in module grenoble), 167
l_to (fortran variable in module logic), 150	licfield (fortran variable in module movie_data), 288
_tomovie (fortran variable in module logic), 151	lip (fortran variable in module precision_mod), 141
l_true_time (fortran variable in module logic), 151	llm (fortran variable in module lmloop_data), 169
l_update_b (fortran variable in module logic), 151	llmmag (fortran variable in module lmloop_data), 169
l_update_s (fortran variable in module logic), 150	lm2 (fortran variable in module blocking), 258
l_update_v (fortran variable in module logic), 151	lm221 (fortran variable in module blocking), 258
_visebecale (fortran variable in module logic), 150	lm22lm (fortran variable in module blocking), 258
l_z10mat (fortran variable in module logic), 150	lm22m (fortran variable in module blocking), 258
lambda (fortran variable in module radial_functions), 185	lm2l (fortran variable in module blocking), 258
lavemem (fortran variable in module truncation), 143	lm2lma (fortran variable in module blocking), 258
Ibdissmean (fortran variable in module output_mod), 264	lm2lmp (fortran variable in module blocking), 258
Ibmat (fortran variable in module matrices), 157	lm2lms (fortran variable in module blocking), 258
ldif (fortran variable in module num_param), 145	lm2lo_redist() (fortran subroutine in module communica-
ldifexp (fortran variable in module num_param), 145	tions), 174
ldtbmem (fortran variable in module truncation), 143	lm2m (fortran variable in module blocking), 258
leg_helper_mod (module), 231	lm2mc (fortran variable in module blocking), 258
legendre_grid_to_spec (module), 239	lm2pt() (fortran subroutine in module out_dtb_frame),
legendre_spec_to_grid (module), 235	322
legprep() (fortran subroutine in module leg_helper_mod),	lm2r_redist_start() (fortran subroutine in module commu-
233	nications), 173
legprep_ic() (fortran subroutine in module	lm2r_redist_wait() (fortran subroutine in module commu-
leg_helper_mod), 234	nications), 173
legprepg() (fortran subroutine in module	lm_max (fortran variable in module truncation), 143
leg helper mod) 232	lm max ave (fortran variable in module truncation), 143

lm_max_dtb (fortran variable in module truncation), 142 lm_max_real (fortran variable in module truncation), 141 lm_maxgeos (fortran variable in module truncation), 142 lm_maxmag (fortran variable in module truncation), 142 lm_on_last_rank (fortran variable in module lm_loop_data), 169 lm_per_rank (fortran variable in module lmloop_data), 169 lmagmem (fortran variable in module truncation), 141 lmas2pt() (fortran subroutine in module legen_dre_spec_to_grid), 239 lmloop() (fortran subroutine in module lmloop_mod), 197	Istart (fortran variable in module horizontal_data), 188 Istartp (fortran variable in module horizontal_data), 188 Istop (fortran variable in module horizontal_data), 188 Istopp (fortran variable in module horizontal_data), 188 Istoremov (fortran variable in module movie_data), 288 Istressmem (fortran variable in module truncation), 142 Itimelimit() (fortran function in module timing), 195 Ivdissmean (fortran variable in module output_mod), 264 Iverbose (fortran variable in module logic), 149 Iwpmat (fortran variable in module matrices), 158 Iz10mat (fortran variable in module matrices), 157 Izmat (fortran variable in module matrices), 158
lmloop_data (module), 169 lmloop_mod (module), 196	M
Immapping (module), 260 Immaxs (fortran variable in module outto_mod), 330 Imodd (fortran variable in module horizontal_data), 188 Imoddp (fortran variable in module horizontal_data), 188 Imoviemem (fortran variable in module truncation), 142 Imp2 (fortran variable in module blocking), 258 Imp2l (fortran variable in module blocking), 258 Imp2lmp (fortran variable in module blocking), 258 Imp2lmpa (fortran variable in module blocking), 258 Imp2lmps (fortran variable in module blocking), 258 Imp2lmps (fortran variable in module blocking), 258 Imp_max (fortran variable in module truncation), 142 Imp_max_dtb (fortran variable in module truncation), 143 Imstartb (fortran variable in module blocking), 258 Instopb (fortran variable in module blocking), 258 Inegtime() (fortran function in module timing), 195 Inpas2tr() (fortran function in module omega), 340 Io2Im_redist() (fortran subroutine in module communications), 174 Io2r_aj (fortran variable in module communications), 171	m_max (fortran variable in module truncation), 142 mag2hint (fortran variable in module rms), 309 magas2hint (fortran variable in module rms), 309 magic (fortran program), 139 magic.bLayers (module), 124 magic.coeff (module), 120 magic.cyl (module), 126 magic.libmagic (module), 131 MagicCoeffCmb (class in magic.coeff), 120 MagicGraph (class in magic), 113 MagicRadial (class in magic), 111 MagicRSpec (class in magic), 121 MagicSetup (class in magic), 109 MagicSpectrum (class in magic), 112 MagicSpectrum2D (class in magic), 113 MagicTs (class in magic), 110 maglmr (fortran variable in module rms), 310 magnetic_energy (module), 268
lo2r_b (fortran variable in module communications), 171 lo2r_p (fortran variable in module communications), 171 lo2r_redist_start() (fortran subroutine in module commu-	mapdatahydro() (fortran subroutine in module readcheck- points), 346 mapdatamag() (fortran subroutine in module readcheck-
nications), 173 lo2r_redist_wait() (fortran subroutine in module communications), 173	points), 347 mapdatar() (fortran subroutine in module readcheck-points), 347
lo2r_s (fortran variable in module communications), 171 lo2r_w (fortran variable in module communications), 171 lo2r_z (fortran variable in module communications), 171 lo_map (fortran variable in module blocking), 258 lo_sub_map (fortran variable in module blocking), 259 log_file (fortran variable in module output_data), 162	mass (fortran variable in module constants), 166 matder() (in module magic.libmagic), 134 matrices (module), 157 maxthreads (fortran variable in module updateb_mod), 207 maxthreads (fortran variable in module updates_mod),
logic (module), <b>149</b> logwrite() (fortran subroutine in module useful), <b>351</b> lorentz_torque_iclast (fortran variable in module field-	204 maxthreads (fortran variable in module updatewp_mod), 199
slast), <b>156</b> lorentz_torque_malast (fortran variable in module field-slast), <b>156</b> lp_file (fortran variable in module output_data), <b>162</b>	maxthreads (fortran variable in module updatez_mod), 202 meantime() (fortran subroutine in module timing), 195 minc (fortran variable in module truncation), 143
lscale (fortran variable in module num_param), 145 lsmat (fortran variable in module matrices), 157	misc_file (fortran variable in module output_data), 161

mode (fortran variable in module physical_parameters), 146	n_cour_step (fortran variable in module num_param), 144 n_dipole_file (fortran variable in module output_data).
Movie (class in magic), 117	160
movie (fortran variable in module movie_data), <b>288</b> Movie3D (class in magic), 119	n_dt_cmb_file (fortran variable in module output_data), 159
movie_const (fortran variable in module movie_data), 288	n_dt_cmb_sets (fortran variable in module output_mod), 265
movie_data (module), 287	n_dtbrms_file (fortran variable in module output_data),
movie_file (fortran variable in module movie_data), 288	161
movie_gather_frames_to_rank0() (fortran subroutine in module movie_data), 295	n_dtdrms_file (fortran variable in module output_data), 160
moviedipcolat (fortran variable in module movie_data), 288	n_dtvasrms_file (fortran variable in module output_data), 162
moviediplon (fortran variable in module movie_data), 288	n_dtvrms_file (fortran variable in module output_data),
moviedipstrength (fortran variable in module movie_data), 288	162 n_e_kin_file (fortran variable in module output_data), 163
moviedipstrengthgeo (fortran variable in module movie_data), 288	n_e_mag_ic_file (fortran variable in module output_data),  160
mpi_def_complex (fortran variable in module precision_mod), 141	n_e_mag_oc_file (fortran variable in module out- put_data), 159
mpi_def_real (fortran variable in module precision_mod), 140	n_e_sets (fortran variable in module output_mod), 264 n_frame_work (fortran variable in module movie_data),
mpi_out_real (fortran variable in module precision_mod), 141	288 n_graph_file (fortran variable in module output_data).
ms2time() (fortran subroutine in module timing), 194	160
msechour (fortran variable in module timing), 194 msecminute (fortran variable in module timing), 194	n_graph_step (fortran variable in module output_data), 162
msecsecond (fortran variable in module timing), 194 mvar (fortran variable in module outpar_mod), 277	n_graphs (fortran variable in module output_data), <b>164</b> n_imp (fortran variable in module bext), <b>165</b>
myallgather() (fortran subroutine in module communications), 174	n_imps (fortran variable in module physical_parameters), 147
N	n_imps_max (fortran variable in module physical_parameters), 148
n_angular_file (fortran variable in module output_data),  164	n_kin_spec_file (fortran variable in module output_data),  160
n_b_r_file (fortran variable in module output_data), 160	n_log_file (fortran variable in module output_data), 162
n_b_r_sets (fortran variable in module output_mod), 265	n_log_step (fortran variable in module output_data), 161
n_bpot_step (fortran variable in module output_data), 160	n_logs (fortran variable in module output_data), 160
n_bpots (fortran variable in module output_data), 162	n_lp_file (fortran variable in module output_data), 159
n_cheb_ic_max (fortran variable in module truncation), 143	n_lscale (fortran variable in module num_param), 144 n_max (fortran variable in module truncation), 142
n_cheb_max (fortran variable in module truncation), 143	n_mag_spec_file (fortran variable in module out-
n_cheb_maxc (fortran variable in module radial_functions), 186	put_data), 160 n_md (fortran variable in module movie_data), 288
n_cmb_file (fortran variable in module output_data), 163	n_misc_file (fortran variable in module output_data), 161
n_cmb_setsmov (fortran variable in module output_mod), 264	n_movie_const (fortran variable in module movie_data), 288
n_cmb_step (fortran variable in module output_data), 163	n_movie_field_start (fortran variable in module
n_cmbmov_file (fortran variable in module output_data), $160$	movie_data), 288 n_movie_field_stop (fortran variable in module
n_cmbs (fortran variable in module output_data), 161	movie_data), 288
n_coeff_r (fortran variable in module output_data), 159	n_movie_field_type (fortran variable in module movie_data), <b>288</b>
n_coeff_r_max (fortran variable in module output_data),	n movie fields (fortran variable in module movie data).

288 n_movie_fields_ic (fortran variable in module	n_r_totmag (fortran variable in module truncation), 142 n_rot_file (fortran variable in module output_data), 160
movie_data), 288 n_movie_fields_max (fortran variable in module	n_rst_file (fortran variable in module output_data), 159 n_rst_step (fortran variable in module output_data), 160
movie_data), 288	n_rsts (fortran variable in module output_data), 160
n_movie_file (fortran variable in module movie_data), 288	n_s_bounds (fortran variable in module init_fields), 178 n_signal_file (fortran variable in module output_data),
n_movie_frames (fortran variable in module output data), 164	n_spec (fortran variable in module output_mod), 264
n_movie_step (fortran variable in module output_data),  163	n_spec_step (fortran variable in module output_data), 164 n_specs (fortran variable in module output_data), 160
n_movie_surface (fortran variable in module	n_sric_file (fortran variable in module output_data), 160
movie_data), 288 n_movie_type (fortran variable in module movie_data),	n_srma_file (fortran variable in module output_data), 160 n_start_file (fortran variable in module init_fields), 178
288	n_stores (fortran variable in module output_data), 162
n_movies (fortran variable in module movie_data), 288	n_t_bpot (fortran variable in module output_data), 162
n_movies_max (fortran variable in module movie_data), 288	n_t_cmb (fortran variable in module output_data), 161 n_t_graph (fortran variable in module output_data), 160
n_par_file (fortran variable in module output_data), 159	n_t_log (fortran variable in module output_data), 161
n_perppar_file (fortran variable in module output_data),  163	n_t_movie (fortran variable in module output_data), 160 n_t_pot (fortran variable in module output_data), 163
n_phi_max (fortran variable in module truncation), 141	n_t_r_field (fortran variable in module output_data), 162
n_phi_maxstr (fortran variable in module truncation), 142	n_t_r_file (fortran variable in module output_data), 163
n_phi_tot (fortran variable in module truncation), 142	n_t_r_sets (fortran variable in module output_mod), 264
n_pot_step (fortran variable in module output_data), 163	n_t_rst (fortran variable in module output_data), 162
n_pots (fortran variable in module output_data), 159	n_t_spec (fortran variable in module output_data), 161
n_power_file (fortran variable in module output_data),	n_t_to (fortran variable in module output_data), 161
161	n_t_tomovie (fortran variable in module output_data),
n_procs (fortran variable in module parallel_mod), 168	161
n_r_array (fortran variable in module output_data), 162	n_t_toz (fortran variable in module output_data), 162
n_r_cmb (fortran variable in module radial_data), 169	n_t_tpot (fortran variable in module output_data), 161
n_r_field_step (fortran variable in module output_data),  164	n_t_vpot (fortran variable in module output_data), <b>164</b> n_theta_cal2ord (fortran variable in module horizon-
n_r_fields (fortran variable in module output_data), 164	tal_data), 188
n_r_ic_max (fortran variable in module truncation), 142 n_r_ic_max_ave (fortran variable in module truncation), 143	n_theta_max (fortran variable in module truncation), 143 n_theta_maxstr (fortran variable in module truncation), 142
n_r_ic_max_dtb (fortran variable in module truncation),	n_time_hits (fortran variable in module output_data), 163
143	n_time_steps (fortran variable in module num_param),
n_r_ic_maxmag (fortran variable in module truncation), 142	145 n_to_step (fortran variable in module output_data), 164
n_r_icb (fortran variable in module radial_data), 168	n_tomovie_frames (fortran variable in module out-
n_r_lcr (fortran variable in module physical_parameters), 148	put_data), <b>159</b> n_tomovie_step (fortran variable in module output_data),
n_r_max (fortran variable in module truncation), 141	162
n_r_max_ave (fortran variable in module truncation), 143	n_tos (fortran variable in module output_data), 160
n_r_max_dtb (fortran variable in module truncation), 142	n_toz_step (fortran variable in module output_data), 160
n_r_maxc (fortran variable in module radial_functions),	n_tozs (fortran variable in module output_data), 162
185	n_tpot_step (fortran variable in module output_data), 162
n_r_maxgeos (fortran variable in module truncation), 142	n_tpots (fortran variable in module output_data), 163
n_r_maxmag (fortran variable in module truncation), 142	n_tscale (fortran variable in module num_param), 144
n_r_maxstr (fortran variable in module truncation), 142	n_u2_spec_file (fortran variable in module output_data),
n r step (fortran variable in module output data) 162	160

n\_r\_tot (fortran variable in module truncation), 143

n_u_square_file (fortran variable in module output_data),	nthetabs (fortran variable in module blocking), 258
160	nthreads (fortran variable in module parallel_mod), 168
n_v_r_file (fortran variable in module output_data), 162	ntomovsets (fortran variable in module output_mod), 264
n_v_r_sets (fortran variable in module output_mod), 265	ntormssets (fortran variable in module output_mod), 264
n_vpot_step (fortran variable in module output_data), 159	ntosets (fortran variable in module output_mod), 264
n_vpots (fortran variable in module output_data), 164	ntpotsets (fortran variable in module output_mod), 264
nalias (fortran variable in module truncation), 143	num_param (module), 144
namelists (module), 174	nvarcond (fortran variable in module physi-
nbdown (fortran variable in module blocking), 258	cal_parameters), 148
nbpotsets (fortran variable in module output_mod), 264	nvardiff (fortran variable in module physical_parameters),  148
nbsave (fortran variable in module blocking), 258 ncp (fortran variable in module truncation), 141	nvareps (fortran variable in module physical_parameters),
nepgeos (fortran variable in module truncation), 143	147
ncut (fortran variable in module radial_functions), 184	nvarvisc (fortran variable in module physi-
nd (fortran variable in module fft_jw), 242	cal_parameters), 148
ndd_costf1 (fortran variable in module radial_functions),	nvpotsets (fortran variable in module output_mod), 264
184	nzmaxa (fortran variable in module output_mod), <b>162</b>
ndd_costfl_ic (fortran variable in module ra-	nzmaxs (fortran variable in module egeos_mod), 333
dial_functions), 185	nzmaxs (fortran variable in module outto_mod), 330
ndd_costf2_ic (fortran variable in module ra-	
dial_functions), 185	0
ndi_costf1 (fortran variable in module radial_functions),	o_r_ic (fortran variable in module radial_functions), 184
185	o_r_ic2 (fortran variable in module radial_functions), 186
ndi_costf1_ic (fortran variable in module ra-	o_sin_theta (fortran variable in module horizontal_data).
dial_functions), 185	188
ndi_costf2_ic (fortran variable in module ra-	o_sin_theta_e2 (fortran variable in module horizon-
dial_functions), 184	tal_data), 188
nfs (fortran variable in module blocking), 258	o_sr (fortran variable in module physical_parameters).
ni (fortran variable in module fft_jw), 242	146
nl_special_calc (module), 340	ohmdissr (fortran variable in module power), 279
nlf (fortran variable in module output_data), 162	ohmlossfac (fortran variable in module physi-
nlmbs (fortran variable in module blocking), 258	cal_parameters), 147
nlmbs2 (fortran variable in module blocking), 258	omega (module), 339
nlmbs_per_rank (fortran variable in module paral-	omega_ic (fortran variable in module fields), 153
lel_mod), 168	omega_ic1 (fortran variable in module init_fields), 179
nlogs (fortran variable in module output_mod), 265	omega_ic2 (fortran variable in module init_fields), 178
nonlinear_bcs (module), 221	omega_ma (fortran variable in module fields), <b>154</b>
nonlinear_lm_mod (module), 219	omega_ma1 (fortran variable in module init_fields), 178
npvsets (fortran variable in module output_mod), 264	omega_ma2 (fortran variable in module init_fields), 179
nr_on_last_rank (fortran variable in module paral-	omegaosz_ic1 (fortran variable in module init_fields), 178
lel_mod), 168	omegaosz_ic2 (fortran variable in module init_fields), 179
nr_per_rank (fortran variable in module parallel_mod), 168	omegaosz_ma1 (fortran variable in module init_fields),
nrms_sets (fortran variable in module output_mod), 264	179
nrotic (fortran variable in module init_fields), 179	omegaosz_ma2 (fortran variable in module init_fields),
nrotma (fortran variable in module init_fields), 179	179
nrp (fortran variable in module truncation), 141	one (fortran variable in module constants), 166
nrpgeos (fortran variable in module truncation), 142	openfiles() (fortran subroutine in module output_data), 164
nrstart (fortran variable in module radial_data), 169	opm (fortran variable in module physical_parameters),
nrstartmag (fortran variable in module radial_data), 169	148
nrstop (fortran variable in module radial_data), 168	opr (fortran variable in module physical_parameters), 149
nrstopmag (fortran variable in module radial_data), 168	or1 (fortran variable in module radial_functions), 185
nsmax (fortran variable in module omega), 340	or2 (fortran variable in module radial_functions), 185
nsmaxa (fortran variable in module output_data), 161	or3 (fortran variable in module radial functions), 185

or4 (fortran variable in module radial_functions), 184 orho1 (fortran variable in module radial_functions), 184 orho2 (fortran variable in module radial_functions), 185 orhoz (fortran variable in module egeos_mod), 333 osints (fortran variable in module egeos_mod), 333 osints (fortran variable in module outpv3), 336 osints (fortran variable in module outto_mod), 330	pdiflm (fortran variable in module dtb_mod), 317 pdiflm_lmloc (fortran variable in module dtb_mod), 317 pdiflmic (fortran variable in module dtb_mod), 317 pdiflmic_lmloc (fortran variable in module dtb_mod), 318 pdifrms (fortran variable in module dtb_mod), 318 peaks (fortran variable in module physical_parameters),  148
osn1 (fortran variable in module horizontal_data), 189	perppar_file (fortran variable in module output_data), 161
osn2 (fortran variable in module horizontal_data), 188	phi (fortran variable in module horizontal_data), 188
osq4pi (fortran variable in module constants), 166	phideravg() (in module magic.libmagic), 134
otemp1 (fortran variable in module radial_functions), 185	phis (fortran variable in module physical_parameters),
out_coeff (module), 302 out_dtb_frame (module), 320	146 physical perspectars (module) 146
out_movie (module), 325	physical_parameters (module), 146 pi (fortran variable in module constants), 166
out_movie_ic (module), 301	plm (fortran variable in module constants), 100 plm (fortran variable in module horizontal_data), 188
out_rms (module), 314	plm_theta() (fortran subroutine in module plms_theta),
outmisc() (fortran subroutine in module outmisc_mod),	230
272	plm_thetaas() (fortran subroutine in module plms_theta),
outmisc_mod (module), 272	230
outomega() (fortran subroutine in module omega), 340	plms (fortran variable in module egeos_mod), 333
outp (fortran variable in module precision_mod), 141	plms (fortran variable in module outpv3), 336
outpar() (fortran subroutine in module outpar_mod), 277	plms (fortran variable in module outto_mod), 330
outpar_mod (module), 276	plms_theta (module), 230
outperppar() (fortran subroutine in module outpar_mod),	plmz (fortran variable in module outpv3), 336
278	plot() (magic.bLayers.BLayers method), 124
output() (fortran subroutine in module nonlin-	plot() (magic.Butterfly method), 131
ear_lm_mod), 220 output() (fortran subroutine in module output_mod), 265	plot() (magic.coeff.MagicCoeffCmb method), 120
output_data (module), 158	plot() (magic.MagicRadial method), 112 plot() (magic.MagicSpectrum method), 112
output_mod (module), 262	plot() (magic.MagicSpectrum2D method), 112
outpv() (fortran subroutine in module outpv3), 336	plot() (magic.MagicTs method), 110
outpv3 (module), 335	plot() (magic.Movie method), 119
outrot (module), 273	plot() (magic.ThetaHeat method), 126
outto() (fortran subroutine in module outto_mod), 330	plot() (magic.TOMovie method), 122
outto_mod (module), 328	plotAvg() (magic.CompSims method), 123
D	plotAvg() (magic.MagicRSpec method), 121
P	plotEmag() (magic.CompSims method), 123
p (fortran variable in module fields), 154	plotEquat() (magic.CompSims method), 123
p_lmloc (fortran variable in module fields), 153	plotFlux() (magic.CompSims method), 123
p_lmloc_container (fortran variable in module fields), 153	plotSurf() (magic.CompSims method), 123
p_rloc (fortran variable in module fields), 154	plotTs() (magic.CompSims method), 123
p_rloc_container (fortran variable in module fields), 154	plotZonal() (magic.CompSims method), 123 polind (fortran variable in module physical_parameters),
padvasrms (fortran variable in module dtb_mod), 317	147
padvlm (fortran variable in module dtb_mod), 317 padvlm_rloc (fortran variable in module dtb_mod), 318	power (module), 278
padvlmic (fortran variable in module dtb_mod), 317	power_file (fortran variable in module output_data), 159
padvlmic_lmloc (fortran variable in module dtb_mod),	pr (fortran variable in module physical_parameters), 148
317	pre (fortran variable in module updatewp_mod), 199
padvrms (fortran variable in module dtb_mod), 318	pre2hint (fortran variable in module rms), 310
par_file (fortran variable in module output_data), 162	preas2hint (fortran variable in module rms), 309
parallel() (fortran subroutine in module parallel_mod),  168	precalc() (fortran subroutine in module precalculations), 182
parallel_mod (module), 167	precalctimes() (fortran subroutine in module precalcula-
pdifasrms (fortran variable in module dtb mod), 317	tions), <b>182</b>

precalculations (module), 181	random() (fortran function in module useful), 350
precision_mod (module), 140	rank_bn (fortran variable in module parallel_mod), 168
prelmr (fortran variable in module rms), 310	rank_with_l1m0 (fortran variable in module paral-
prmag (fortran variable in module physical_parameters),	lel_mod), 168
148	rascaled (fortran variable in module physi-
progressbar() (in module magic.libmagic), 135	cal_parameters), 147
pscale (fortran variable in module num_param), 145	rbpspec() (fortran subroutine in module radial_spectra),
pstrasrms (fortran variable in module dtb_mod), 317	332
pstrlm (fortran variable in module dtb_mod), 317	rbrspec() (fortran subroutine in module radial_spectra),
pstrlm_rloc (fortran variable in module dtb_mod), 318	332
pstrrms (fortran variable in module dtb_mod), 317	rc (fortran variable in module radial_functions), 185
n	rcut (fortran variable in module output_data), 163
R	rdea (fortran variable in module output_data), 161
r (fortran variable in module radial_functions), 186	rderavg() (in module magic.libmagic), 135
r2lm_redist() (fortran subroutine in module communica-	readcheckpoints (module), 344
tions), 173	readhdf5_attr_dble() (fortran subroutine in module
r2lo_redist() (fortran subroutine in module communica-	hdf5helpers), 354
tions), 174	readhdf5_attr_int() (fortran subroutine in module
r_cmb (fortran variable in module radial_functions), 184	hdf5helpers), 354
r_cut_model (fortran variable in module physi-	readhdf5_attribute (fortran variable in module
cal_parameters), 147	hdf5helpers), 353
r_ic (fortran variable in module radial_functions), 185	readnamelists() (fortran subroutine in module namelists),
r_icb (fortran variable in module radial_functions), 184	175
r_lcr (fortran variable in module physical_parameters),	readstartfields() (fortran subroutine in module readcheck-
146	points), <b>345</b>
r_lm_gather_type (fortran variable in module communi-	rearangeLat() (magic.MagicGraph method), 114
cations), 171	rgrav (fortran variable in module radial_functions), 184
r_lm_gather_type_lm_end (fortran variable in module	rho0 (fortran variable in module radial_functions), 184
communications), 171	rho_ratio_ic (fortran variable in module physi-
r_request (fortran variable in module communications),	cal_parameters), 147
171	rho_ratio_ma (fortran variable in module physi-
r_surface (fortran variable in module radial_functions),	cal_parameters), 147
185	rhoz (fortran variable in module egeos_mod), 333
r_transfer_type (fortran variable in module communica-	rhs1 (fortran variable in module updateb_mod), 207
tions), <b>171</b>	rhs1 (fortran variable in module updates_mod), 204
r_transfer_type_cont (fortran variable in module commu-	rhs1 (fortran variable in module updatewp_mod), 199
nications), 171	rhs1 (fortran variable in module updatez_mod), 201
r_transfer_type_nr_end (fortran variable in module com-	rhs2 (fortran variable in module updateb_mod), 207
munications), 171	rint() (fortran function in module integration), 256
r_transfer_type_nr_end_cont (fortran variable in module	rint_r() (fortran function in module integration), 256
communications), 171	rintic() (fortran function in module integration), 256
ra (fortran variable in module physical_parameters), 146	riteration_mod (module), 211
radial() (fortran subroutine in module radial_functions),	riterthetablocking_mod (module), 213
186	riterthetablocking_openmp_mod (module), 215
radial_data (module), 168	rmmean (fortran variable in module output_mod), 264
radial_der (module), 248	rmmeanr (fortran variable in module outpar_mod), 277
radial_der_even (module), 252	rms (module), 308
radial_functions (module), 183	rms_helpers (module), 311
radial_spectra (module), 331	rolmean (fortran variable in module output_mod), 264
radialloop (module), 209	rolmeanr (fortran variable in module outpar_mod), 277
radialloopg() (fortran subroutine in module radialloop),	rolmeanru2 (fortran variable in module outpar_mod), 277
209	rot_file (fortran variable in module output_data), 161
radratio (fortran variable in module physical_parameters),	rrmp (fortran variable in module bext), 165
148	rst_file (fortran variable in module output_data), 161

rst_mpi_fh (fortran variable in module output_data), 163 rstrm (fortran variable in module output_data), 330 runid (fortran variable in module output_data), 160 runtime (fortran variable in module num_param), 144 runtimelimit (fortran variable in module num_param), 145 runtimestart (fortran variable in module num_param), 144 rz (fortran variable in module egeos_mod), 333 rz (fortran variable in module outpv3), 336	set_zero() (fortran subroutine in module nonlinear_lm_mod), 220 sgefa() (fortran subroutine in module algebra), 247 sgesl() (fortran subroutine in module algebra), 247 sigma (fortran variable in module radial_functions), 186 sigma_ratio (fortran variable in module physical_parameters), 147 sin36 (fortran variable in module constants), 166 sin60 (fortran variable in module constants), 166
rz (fortran variable in module outto_mod), 330	sin72 (fortran variable in module constants), <b>166</b>
S	sintheta (fortran variable in module horizontal_data), 188
s (fortran variable in module fields), 155	sizelmb (fortran variable in module blocking), 258 sizelmb2 (fortran variable in module blocking), 258
s0mat (fortran variable in module matrices), 157 s0mat_fac (fortran variable in module matrices), 157	sizeof_character (fortran variable in module precision_mod), 141
s0pivot (fortran variable in module matrices), 158	sizeof_def_complex (fortran variable in module precision_mod), 140
s_ave (fortran variable in module fields_average_mod), 307	sizeof_def_real (fortran variable in module preci-
s_ave_global (fortran variable in module fields_average_mod), 307	sion_mod), <b>141</b> sizeof_integer (fortran variable in module preci-
s_bot (fortran variable in module init_fields), 179	sion_mod), 141
s_cond() (fortran subroutine in module init_fields), <b>181</b> s_lmloc (fortran variable in module fields), <b>155</b>	sizeof_out_real (fortran variable in module precision_mod), <b>141</b>
s_lmloc_container (fortran variable in module fields), 153	sizerb (fortran variable in module blocking), 258
s_request (fortran variable in module communications),	sizethetab (fortran variable in module blocking), 258 sizethetabi (fortran variable in module blocking), 258
171 s_rloc (fortran variable in module fields), 153	slice() (magic.cyl.Cyl method), 128
s_rloc_container (fortran variable in module fields), 155	slice() (magic.Surf method), 116
s_top (fortran variable in module init_fields), 179	slopestrat (fortran variable in module physi-
s_transfer_type (fortran variable in module communica-	cal_parameters), 146
tions), <b>171</b>	smat (fortran variable in module matrices), 158
s_transfer_type_cont (fortran variable in module commu-	smat_fac (fortran variable in module matrices), 157 smeanr (fortran variable in module outpar_mod), 277
nications), 171 s_transfer_type_nr_end (fortran variable in module com-	sn2 (fortran variable in module horizontal_data), 188
munications), 171	sn_sub_map (fortran variable in module blocking), 258
s_transfer_type_nr_end_cont (fortran variable in module	spectra (module), 280
communications), 171	spectrum() (fortran subroutine in module spectra), 283
safeclose() (fortran subroutine in module useful), 351 safeopen() (fortran subroutine in module useful), 351	spectrum_average() (fortran subroutine in module spectra), 282
scale_b (fortran variable in module init_fields), 179	spectrum_temp() (fortran subroutine in module spectra), 283
scale_s (fortran variable in module init_fields), 178 scale_v (fortran variable in module init_fields), 179	spectrum_temp_average() (fortran subroutine in module
scanDir() (in module magic.libmagic), 135	spectra), 283
scatter_from_rank0_to_lo() (fortran subroutine in module	sph2cyl() (in module magic.cyl), 128
communications), 173	sph2cyl_plane() (in module magic.cyl), 129
sdens (fortran variable in module output_data), 163	spivot (fortran variable in module matrices), <b>157</b> sq4pi (fortran variable in module constants), <b>166</b>
sderavg() (in module magic.libmagic), 135	sric_file (fortran variable in module output_data), 163
selectField() (in module magic.libmagic), 136 sendvals_to_rank0() (fortran subroutine in module out-	srma_file (fortran variable in module output_data), 162
rot), 275	st_map (fortran variable in module blocking), 258
set_steering_variables() (fortran subroutine in module rit-	st_sub_map (fortran variable in module blocking), 258
eration_mod), 212	start_fields (module), 176
set_thetablocking() (fortran subroutine in module riter-thetablocking_mod), 214	start_file (fortran variable in module init_fields), 179

step_time_mod), 191	t_log_start (fortran variable in module output_data), 163 t_log_stop (fortran variable in module output_data), 159
step_time_mod (module), 189	t_movie (fortran variable in module output_data), 161
store() (fortran subroutine in module storecheckpoints), 348	t_movie_start (fortran variable in module output_data),  161
store_fields_3d() (fortran subroutine in module out_movie), 300	t_movie_stop (fortran variable in module output_data), 161
store_fields_p() (fortran subroutine in module out_movie), 298	t_movies (fortran variable in module movie_data), 288 t_pot (fortran variable in module output_data), 161
store_fields_r() (fortran subroutine in module out_movie), 297	t_pot_start (fortran variable in module output_data), 160 t_pot_stop (fortran variable in module output_data), 162
store_fields_sur() (fortran subroutine in module out_movie), 297	t_r_field (fortran variable in module output_data), 160 t_r_field_start (fortran variable in module output_data),
store_fields_t() (fortran subroutine in module out_movie), 299	159 t_r_field_stop (fortran variable in module output_data),
store_movie_frame() (fortran subroutine in module out_movie), 296	163 t_r_file (fortran variable in module output_data), 161
store_movie_frame_ic() (fortran subroutine in module out_movie_ic), 302	t_rst (fortran variable in module output_data), 163 t_rst_start (fortran variable in module output_data), 160
store_pot_mod (module), 305	t_rst_stop (fortran variable in module output_data), 159
storecheckpoints (module), 348	t_spec (fortran variable in module output_data), 163
storepot() (fortran subroutine in module store_pot_mod),	t_spec_start (fortran variable in module output_data), 160
305	t_spec_stop (fortran variable in module output_data), 164
storepotw() (fortran subroutine in module	t_to (fortran variable in module output_data), 162
store_pot_mod), 306	t_to_start (fortran variable in module output_data), 163
str2dble() (fortran subroutine in module charmanip), 352	t_to_stop (fortran variable in module output_data), 161
strat (fortran variable in module physical_parameters),	t_tomovie (fortran variable in module output_data), <b>161</b>
146	t_tomovie_start (fortran variable in module output_data),
strm (fortran variable in module outto_mod), 330	162
subtime() (fortran subroutine in module timing), 195	t_tomovie_stop (fortran variable in module output_data),
Surf (class in magic), 114	161
surf() (magic.cyl.Cyl method), 128	t_toz (fortran variable in module output_data), 162
surf() (magic.Surf method), 117	t_toz_start (fortran variable in module output_data), 162
surf_cmb (fortran variable in module constants), 166	t_toz_stop (fortran variable in module output_data), 163
svar (fortran variable in module outpar_mod), 277	t_tpot (fortran variable in module output_data), 163
symmetrize() (in module magic.libmagic), 136	t_tpot_start (fortran variable in module output_data), 161
Т	t_tpot_stop (fortran variable in module output_data), 161
	t_vpot (fortran variable in module output_data), 160
t2_ave (fortran variable in module spectra), 282	t_vpot_start (fortran variable in module output_data), 160 t_vpot_stop (fortran variable in module output_data), 163
t_ave (fortran variable in module spectra), 281	tadvasrms (fortran variable in module dtb_mod), 317
t_bpot (fortran variable in module output_data), 162	tadvlm (fortran variable in module dtb_mod), 317
t_bpot_start (fortran variable in module output_data), 159	tadvim_rloc (fortran variable in module dtb_mod), 317
t_bpot_stop (fortran variable in module output_data), 161	tadvlmic (fortran variable in module dtb_mod), 317
t_cmb (fortran variable in module output_data), 160	tadvlmic_lmloc (fortran variable in module dtb_mod),
t_cmb_start (fortran variable in module output_data), 163 t_cmb_stop (fortran variable in module output_data), 163	317
t_graph (fortran variable in module output_data), 162	tadvrlm (fortran variable in module dtb_mod), 317
t_graph_start (fortran variable in module output_data),	tadvrlm_rloc (fortran variable in module dtb_mod), 317
159	tadvrms (fortran variable in module dtb_mod), 318
t_graph_stop (fortran variable in module output_data),	tag (fortran variable in module output_data), 162
163	tdifasrms (fortran variable in module dtb_mod), 317
t_icb2_ave (fortran variable in module spectra), 282	tdiflm (fortran variable in module dtb_mod), 318
t_icb_ave (fortran variable in module spectra), 281	tdiflm_lmloc (fortran variable in module dtb_mod), 317
t log (fortran variable in module output data) 161	tdiflmic (fortran variable in module dtb mod), 317

tdiflmic_lmloc (fortran variable in module dtb_mod), 318 tdifrms (fortran variable in module dtb_mod), 317 temp0 (fortran variable in module radial_functions), 185 temp_gather_lo (fortran variable in module communications), 171 temp_r2lo (fortran variable in module communications),	tshift_ma1 (fortran variable in module init_fields), 178 tshift_ma2 (fortran variable in module init_fields), 178 tstrasrms (fortran variable in module dtb_mod), 317 tstrlm (fortran variable in module dtb_mod), 318 tstrlm_rloc (fortran variable in module dtb_mod), 317 tstrrlm (fortran variable in module dtb_mod), 318
171	tstrrlm_rloc (fortran variable in module dtb_mod), 318
tend (fortran variable in module num_param), 145	tstrrms (fortran variable in module dtb_mod), 317
theta (fortran variable in module horizontal_data), 188	two (fortran variable in module constants), <b>166</b>
theta_ord (fortran variable in module horizontal_data), 188	U
thetaderavg() (in module magic.libmagic), 136 ThetaHeat (class in magic), 125	u_square_file (fortran variable in module output_data), 163
thetas (fortran variable in module physical_parameters),	uhmeanr (fortran variable in module outpar_mod), 277
147	ulm (fortran variable in module lmloop_data), 169
third (fortran variable in module constants), 166	ulmmag (fortran variable in module lmloop_data), 169
three (fortran variable in module constants), 165	unknown_type (fortran type in module communications),
time2ms() (fortran function in module timing), 194	170
timenormlog (fortran variable in module output_mod), $264$	unknown_type (fortran type in module gen- eral_arrays_mod), 219
timepassedlog (fortran variable in module output_mod), 264	unknown_type (fortran type in module leg_helper_mod), 232
timestart (fortran variable in module num_param), 144	unknown_type (fortran type in module lmmapping), 260
timing (module), 194	unknown_type (fortran type in module nonlin-
tipdipole (fortran variable in module init_fields), 179	ear_lm_mod), <b>220</b>
tmagcon (fortran variable in module physi-	unknown_type (fortran type in module riteration_mod),
cal_parameters), 148 to_gather_rloc_on_rank0() (fortran subroutine in module	211
torsional_oscillations), 327	unknown_type (fortran type in module riterthetablock-
to_helpers (module), 327	ing_mod), 213, 214
tomeasrms (fortran variable in module dtb_mod), 317	unknown_type (fortran type in module riterthetablock-ing_openmp_mod), 216
tomega_ic1 (fortran variable in module init_fields), 179	updateb() (fortran subroutine in module updateb_mod),
tomega_ic2 (fortran variable in module init_fields), 179	207
tomega_ma1 (fortran variable in module init_fields), 178	updateb_mod (module), 206
tomega_ma2 (fortran variable in module init_fields), 178	updates() (fortran subroutine in module updates_mod),
tomelm (fortran variable in module dtb_mod), 318	204
tomelm_rloc (fortran variable in module dtb_mod), 317 tomerlm (fortran variable in module dtb_mod), 317	updates_ala() (fortran subroutine in module updates_mod), 205
tomerlm_rloc (fortran variable in module dtb_mod), 318	updates_mod (module), 203
tomerms (fortran variable in module dtb_mod), 317	updatewp() (fortran subroutine in module up-
TOMovie (class in magic), 122	datewp_mod), 199
topcond (fortran variable in module radial_functions), 184	updatewp_mod (module), 198
tops (fortran variable in module init_fields), 179	updatez() (fortran subroutine in module updatez_mod),
torsional_oscillations (module), 323	202
transform_to_grid_space() (fortran subroutine in module	updatez_mod (module), 200
riterthetablocking_mod), 214	useful (module), 349
transform_to_lm_space() (fortran subroutine in module	
riterthetablocking_mod), 215	V
transportproperties() (fortran subroutine in module ra-	v2as (fortran variable in module torsional_oscillations),
dial_functions), 186	324
truncation (module), 141	v2as_rloc (fortran variable in module tor-
tscale (fortran variable in module num_param), 145	sional_oscillations), 325
tshift_ic1 (fortran variable in module init_fields), 179 tshift_ic2 (fortran variable in module init_fields), 179	v_r_file (fortran variable in module output_data), 164

v_rigid_boundary() (fortran subroutine in module nonlinear_bcs), 222	writehdf5_attr_dble() (fortran subroutine in module hdf5helpers), <b>354</b>
visc (fortran variable in module radial_functions), <b>184</b> vischeatfac (fortran variable in module physi-	writehdf5_attr_int() (fortran subroutine in module hdf5helpers), <b>354</b>
cal_parameters), 148	writehdf5_attribute (fortran variable in module
vol_ic (fortran variable in module constants), 166	hdf5helpers), 353
vol_oc (fortran variable in module constants), 166	writeinfo() (fortran subroutine in module precalculations)
vorold (fortran variable in module outpv3), 336	183
vpm (fortran variable in module outto_mod), 330	writenamelists() (fortran subroutine in module namelists)
vscale (fortran variable in module num_param), 145	writetime() (fortran subroutine in module timing), 196
W	writeVpEq() (in module magic.libmagic), 136
w (fortran variable in module fields), 154	V
w_ave (fortran variable in module fields_average_mod), 307	Y y10_norm (fortran variable in module constants), 166
	· ·
w_ave_global (fortran variable in module fields_average_mod), 307	y11_norm (fortran variable in module constants), <b>166</b>
w_lmloc (fortran variable in module fields), 155	Z
w_lmloc_container (fortran variable in module fields), 153	z (fortran variable in module fields), <b>153</b> z10mat (fortran variable in module matrices), <b>157</b>
w_rloc (fortran variable in module fields), 154	z10mat_fac (fortran variable in module matrices), <b>157</b>
w_rloc_container (fortran variable in module fields), <b>154</b>	z10pivot (fortran variable in module matrices), <b>157</b>
walltime() (fortran subroutine in module timing), 194	z_ave (fortran variable in module fields_average_mod)
widths (fortran variable in module physical_parameters),	307
146	z_ave_global (fortran variable in module
worka (fortran variable in module updateb_mod), 207	fields_average_mod), 307
worka (fortran variable in module updates_mod), 204	z_lmloc (fortran variable in module fields), <b>154</b>
worka (fortran variable in module updatewp_mod), 199	z_lmloc_container (fortran variable in module fields), 154 z_lmloc_container (fortran variable in module fields), 155
worka (fortran variable in module updatez_mod), 201	z_rloc (fortran variable in module fields), 154
workb (fortran variable in module updateb_mod), 207	
workb (fortran variable in module updates_mod), 204	z_rloc_container (fortran variable in module fields), 154
workb (fortran variable in module updatewp_mod), 199	zavg() (in module magic.cyl), 129
workb (fortran variable in module updatez_mod), 201	zdens (fortran variable in module output_data), 159
worke (fortran variable in module updatez_mod), 201	zderavg() (in module magic.libmagic), 137
wpass2jw() (fortran subroutine in module fft_jw), 244	zero (fortran variable in module constants), 166
wpass3jw() (fortran subroutine in module fit_jw), 244	zero_tolerance (fortran variable in module algebra), 246
	zerorms() (fortran subroutine in module rms), 310
wpass4jw() (fortran subroutine in module fft_jw), 245 wpass5jw() (fortran subroutine in module fft_jw), 245	zmat (fortran variable in module matrices), 157
	zmat_fac (fortran variable in module matrices), 157
wplm (fortran variable in module horizontal_data), 188	zpivot (fortran variable in module matrices), 157
wpmat (fortran variable in module matrices), 157	zz (fortran variable in module egeos_mod), 333
wpmat_fac (fortran variable in module matrices), 157	zz (fortran variable in module outto_mod), 330
wppivot (fortran variable in module matrices), 158	
write_bcmb() (fortran subroutine in module out_coeff), 303	
write_coeff_r() (fortran subroutine in module out_coeff), 303	
write_dataset() (fortran subroutine in module hdf5helpers), 353	
write_dtb_frame() (fortran subroutine in module out_dtb_frame), 321	
write_movie_frame() (fortran subroutine in module out_movie), 297	
write_rot() (fortran subroutine in module outrot) 274	