

MAGIC Documentation

Release 5.6

The MAGIC dev team

CONTENTS

1	Introduction	1			
	1.1 Foreword	1			
	1.2 Giving credit	2			
2	Get MagIC and run it	3			
	2.1 Download the code	3			
	2.2 Setting up the environment variables	3			
	2.3 Setting up compiler options and compiling	4			
	2.4 Preparing a production run	6			
3	Formulation of the (magneto)-hydrodynamics problem	7			
	3.1 The reference state	8			
	3.2 Boussinesq approximation	10			
	3.3 Anelastic approximation	11			
	3.4 Dimensionless control parameters	14			
	3.5 Boundary conditions and treatment of inner core	15			
4	Numerical technique	17			
	4.1 Poloidal/toroidal decomposition	17			
	4.2 Spherical harmonic representation	18			
	4.3 Radial representation	21			
	4.4 Spectral equations	22			
	4.5 Time-stepping schemes	27			
	4.6 Coriolis force and nonlinear terms	29			
	4.7 Boundary conditions and inner core	35			
5	Contributing to the code 4				
	5.1 Checking the consistency of the code	41			
	5.2 Advices when contributing to the code	42			
	5.3 Building the documentation and contributing to it	43			
6	Input parameters	45			
	6.1 Grid namelist	47			
	6.2 Control namelist	48			
	6.3 Physical parameters namelist	52			
	6.4 External Magnetic Field Namelist	60			
	6.5 Start field namelist	61			
	6.6 Output control namelist	64			
	6.7 Mantle and Inner Core Namelists	77			
7	Interactive communication with the code using signal. TAG	81			

8	Outp	ut files	83
	8.1	Log file: log.TAG	85
	8.2	Default time-series outputs	85
	8.3	Additional optional time-series outputs	
	8.4	Time-averaged radial profiles	97
	8.5	Transport properties of the reference state	
	8.6	Nonlinear mapping of the Chebyshev grid	105
	8.7	Spectra	105
	8.8	Graphic files G_#.TAG and G_ave.TAG	110
	8.9	Movie files *_mov.TAG	117
	8.10	Restart files checkpoint_*.TAG	120
	8.11	Poloidal and toroidal potentials at given depths	
	8.12	TO outputs	
	8.13	Radial spectra rB[r p]Spec.TAG	
	8.14	Potential files [V B T]_lmr_#.TAG	
	0.1	Totalian med [v B T]_ImT_#*ITO	12)
9	Data	visualisation and post-processing	135
	9.1	Requirements	135
	9.2	Configuration: magic.cfg file	
	9.3	Python functions and classes	
		•	
10	Desci	ription of the Fortran modules	181
	10.1	Main program magic.f90	181
	10.2	Base modules	
	10.3	MPI related modules	
	10.4		
		Pre-calculations	
	10.6	Time stepping	
		Linear calculation part of the time stepping (LMLoop)	
		Non-linear part of the time stepping (radial loop)	
		Chebyshev polynomials and cosine transforms	
		Legendre transforms	
		Fourier transforms	
		Linear algebra	
		Radial derivatives and integration	
		Blocking and LM mapping	
		IO: time series, radial profiles and spectra	
		IO: graphic files, movie files, coeff files and potential files	
		IO: RMS force balance, torsional oscillations, misc	
		Reading and storing check points (restart files)	415
	10.19	Useful additional libraries	422
Fo	rtran l	Module Index	431
Рy	thon N	Module Index	433
	dev		435

INTRODUCTION

1.1 Foreword

MagIC is a numerical code that can simulate fluid dynamics in a spherical shell. MagIC solves for the Navier-Stokes equation including Coriolis force, optionally coupled with an induction equation for Magneto-Hydro Dynamics (MHD), a temperature (or entropy) equation and an equation for chemical composition under both the anelastic and the Boussinesq approximations.

MagIC uses Chebyshev polynomials in the radial direction and spherical harmonic decomposition in the azimuthal and latitudinal directions. The time-stepping scheme relies on a semi-implicit Crank-Nicolson for the linear terms of the MHD equations and a Adams-Bashforth scheme for the non-linear terms and the Coriolis force.

MagIC is written in Fortran and designed to be used on supercomputing clusters. It thus relies on a hybrid parallelisation scheme using both OpenMP and MPI. Postprocessing functions written in python (requiring matplotlib and scipy) are also provided to allow a useful data analysis.




Fig. 1.1: Mean walltime of the MagIC code on the supercomputer stampede versus number of CPUs for a dynamo model computed at three different numerical resolutions $(N_{\phi}, N_{\theta}, N_r)$. The solid black lines show the ideal scalings.

MagIC is a free software. It can be used, modified and redistributed under the terms of the GNU GPL v3 licence.

1.2 Giving credit

In case you intend to publish scientific results obtained with the MagIC code or present them in a conference, we (the developers of MagIC) kindly ask to be acknowledged with a reference to the website https://magic-sph.github.io/ or https://github.com/magic-sph/magic.

We also suggest to give appropriate reference to one or several of the following papers:

- Boussinesq equations: Wicht (2002, PEPI, 132, 281-302)
- Anelastic equations: Gastine & Wicht (2012, Icarus, 219, 28-442)
- Boussinesq benchmark: Christensen et al. (2001, PEPI, 128, 25-34)
- Benchmark for double diffusive convection: Breuer et al. (2010, GJI, 183, 150-162)
- Anelastic benchmark: Jones et al. (2011, Icarus, 216, 120-135)
- In case you use the SHTns library for the spherical harmonics transforms (MagIC 5.3 or later), please also cite: Schaeffer (2013, GGG, 14, 751-758)

See also:

A (tentative) comprehensive list of the publications that have been produced to date (october 2015) using **MagIC** is accessible here. To date, more than **70 publications** have been-accepted in more than 10 different peer-reviewed journals: PEPI (19), Icarus (10), E&PSL (6), GJI (6), A&A (4), GRL (4), JFM (3), GAFD (3), Nature (2), etc.




Fig. 1.2: Number of peer-reviewed publications produced using MagIC

CHAPTER

TWO

GET MAGIC AND RUN IT

2.1 Download the code

You can download a snapshot of the code from the Git repository using

```
$ git clone https://github.com/magic-sph/magic.git
```

In case you already have an account on github.com and uploaded a public SSH key on it, you could then rather use SSH:

```
$ git clone ssh://git@github.com/magic-sph/magic.git
```

2.2 Setting up the environment variables

Although not mandatory, it is strongly recommended to correctly source the environment variables of the MagIC code. It will ensure a smoother usage of the post-processing *python classes* and allow to run the *auto-test suite*. To do that, just go to the root directory of the MagIC code (magic) and source sourceme file that corresponds to your \$SHELL environment variable.

In case you use bash, ksh or zsh, just use:

```
$ source sourceme.sh
```

In case you use csh or tcsh, rather use

```
$ source sourceme.csh
```

You can make sure that the environment variables have been correctly sourced by typing:

```
$ echo $MAGIC_HOME
$ echo $PYTHONPATH
```

If you don't want to source sourceme.[c]sh on each session, you can add the following into your . bash_profile (or .profile or .zprofile or .cshrc):

```
$ source whereverYouCheckedOut/magic/sourceme.sh
```

To get started, you then need to compile the code.

2.3 Setting up compiler options and compiling

The **recommended way of compiling MagIC** is to use the build system CMake, if available on your platform. Otherwise, a backup solution is provided via the manual edition of a Makefile.

2.3.1 Generic compiling options

For both build systems (CMake or make), several build options can be toggled using the following available options:

- ARCH Set it to '64' for 64 bit architecture or to '32' for 32 bit architecture
- PRECISION Set it to 'dble' for double-precision calculations or to 'sngl' for single-precision calculations
- OUT_PREC Set it to 'dble' for double-precision in binary outputs or to 'sngl' for single precision
- USE_MPI Set to yes to use MPI, set it to no if you want a serial version of the code .
- USE_OMP Set it to yes to use the hybrid version of the code, or to no for a pure MPI (or serial) version.
- USE_PRECOND Set to yes to perform some pre-conditioning of the matrices.
- USE_FFTLIB This option lets you select the library you want to use for Fast Fourier Transforms. This can be set to 'JW' or 'MKL'. 'JW' refers to the inbuilt library by **J** ohannes **W** icht, while 'MKL' refers to the Intel Math Kernel Library. Use 'JW' if you don't have Intel MKL installed.
- USE_LAPACKLIB This option allows you to select the library you want to use for LU factorisation. This can be set to 'JW', 'MKL' or 'LAPACK'. 'JW' refers to the built-in library, while 'MKL' refers to the Intel Math Kernel Library and 'LAPACK' to the Lapack library
- USE_SHTNS Set to yes to use SHTns library for spherical harmonics transforms. The helper script install-shtns.sh is available in the bin directory to help installing SHTns.
- CMAKE_BUILD_TYPE Set to Debug to enable the full debug flags.

Warning: MagIC cannot run with openMP alone, therefore a configuration of the form USE_MPI=no, USE_OMP=yes will be overwritten to force USE_OMP=no

2.3.2 Using CMake (recommended)

CMake is a powerful tool that can automatically detects and finds the best appropriate configuration for your platform. To use it, you just need to create a directory where you want to build the sources. For instance:

```
$ mkdir $MAGIC_HOME/build
$ cd $MAGIC_HOME/build
```

In a second step, you might want to specify your C and Fortran compilers (in case you skip this step, CMake will look for compilers for you but it might pick up another compiler as the one you might have wanted). For instance, in case you want to use the Intel compilers, you can export the following environment variables

```
$ export FC=mpiifort
$ export CC=mpiicc
```

for bash/ksh/zsh users and

```
$ setenv FC=mpiifort
$ setenv CC=mpiicc
```

for csh/tcsh users. At this stage you should be ready to build the code. If you simply use:

```
$ cmake ..
```

CMake will try to use the best options available on your machine (for instance it will try to locate and link the Intel Math Kernel Library). Otherwise you can pass the aforementioned available options to CMake using the generic form -DOPTION=value. For instance, in case you want to make use of the built-in libraries of MagIC and want to disable OpenMP, simply use

```
$ cmake .. -DUSE_OMP=no -DUSE_FFTLIB=JW -DUSE_LAPACKLIB=JW
```

Once you're happy with your configuration, just compile the code:

```
$ make -j
```

The executable magic.exe should have been produced in the local directory.

If you want to recompile the code from scratch do

```
$ make clean
```

to remove all the files generated by the compiler.

Once the executable is built, you are now ready to run your first production run!

2.3.3 Using make (backup solution)

In case CMake is not available on your platform, it is still possible to compile the code directly. Go to the directory where the source files of MagIC are contained

```
$ cd $MAGIC_HOME/src
```

Select compiler

Edit the file named Makefile using your favourite editor and set a suitable compiler for your platform using the variable: COMPILER = value. The possible options are intel, gnu or portland compilers.

List of default compilers

Compiler Option	Normal	With MPI	
intel	ifort, icc	mpiifort, mpiicc	
gnu	gfortran, gcc	mpif90, mpicc	
portland	pgf95, pgcc	mpif90, mpicc	

Warning: In case you want to use intel but mpiifort and mpiicc are not available, you may also need to adapt the variables COMP_MPFC and COMP_MPCC.

Select compiling options

You can also modify the different compiling options by editing the values of the various parameters defined in the first lines of the Makefile. For instance, in case you want to make use of the built-in libraries and want to disable OpenMP, just define

```
USE_OMP=no
USE_FFTLIB=JW
USE_LAPACKLIB=JW
```

MPI INCPATH

This variable sets the path for your MPI header file mpif.h. This is in general useless if you already use the MPI wrappers such as mpiifort or mpif90 to compile the code. It might be however required to define this path for some compiler configurations: MPI_INCPATH is usually /usr/include or /usr/include/mpi and should be found by the Makefile automatically thanks to the command mpif90 —-showme:incdirs. In case this doesn't work, you may need to specify this variable manually in the Makefile. On supercomputing clusters, this variable is in general not used.

Other compilers

If your available compilers are different from the options provided in the Makefile, then just create a new profile for your desired compiler by changing the options COMP_FC and COMP_CC for serial fortran and C compilers and COMP_MPFC and COMP_MPCC for the possible MPI wrappers.

Once you've set up your compiling options compile the code using

```
$ make -j
```

The compiler should then produce an executable named magic.exe.

If you want to recompile the code from scratch do

```
$ make clean
```

to remove all the files generated by the compiler.

Once the executable is built, you are now ready to run your first production run!

2.4 Preparing a production run

After building the executable, use one of the namelists provided in the $MAGIC_HOME/samples$ directory (called input.nml), adapt it to your physical problem (see *here* for an exhaustive description of the possible options) and run **MagIC** as follows:

• Running a serial version of the code (USE_MPI=no and USE_OMP=no):

```
$ ./magic.exe input.nml
```

• Running the code without OpenMP (USE_MPI=yes and USE_OMP=no) with <n_mpi> MPI ranks:

```
$ mpiexec -n <n_mpi> ./magic.exe input.nml
```

• Running the hybrid code (USE_MPI=yes and USE_OMP=yes) with <n_mpi> MPI ranks and <n_omp> OpenMP threads:

```
$ export OMP_NUM_THREAD = <n_omp>
$ export KMP_AFFINITY=verbose,granularity=core,compact,1
$ mpiexec -n <n_mpi> ./magic.exe input.nml
```

Note that the n_r_max-1 must be a multiple of $n_mpi>$, where n_r_max is the number of radial grid points (see *here*).

FORMULATION OF THE (MAGNETO)-HYDRODYNAMICS PROBLEM

The general equations describing thermal convection and dynamo action of a rotating compressible fluid are the starting point from which the Boussinesq or the anelastic approximations are developed. In MagIC, we consider a spherical shell rotating about the vertical z axis with a constant angular velocity Ω . Equations are solve in the corotating system.

The conservation of momentum is formulated by the Navier-Stokes equation

$$\rho \left(\frac{\partial \boldsymbol{u}}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \, \boldsymbol{u} \right) = -\boldsymbol{\nabla} p + \frac{1}{\mu_0} (\boldsymbol{\nabla} \times \boldsymbol{B}) \times \boldsymbol{B} + \rho \boldsymbol{g} - 2\rho \boldsymbol{\Omega} \times \boldsymbol{u} + \boldsymbol{\nabla} \cdot \boldsymbol{S}, \tag{3.1}$$

where u is the velocity field, B the magnetic field, and p a modified pressure that includes centrifugal forces. S corresponds to the rate-of-strain tensor given by:

$$S_{ij} = 2\nu\rho \left[e_{ij} - \frac{1}{3}\delta_{ij} \nabla \cdot \boldsymbol{u} \right],$$

$$e_{ij} = \frac{1}{2} \left(\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right).$$

Convection is driven by buoyancy forces acting on variations in density ρ . These variations have a dynamical part formulated by the continuity equation describing the conservation of mass:

$$\frac{\partial \rho}{\partial t} = -\nabla \cdot \rho \boldsymbol{u}.\tag{3.2}$$

In addition an equation of state is required to formulate the thermodynamic density changes. For example the relation

$$\frac{1}{\rho}\partial\rho = -\alpha\partial T + \beta\partial p - \delta\partial\xi\tag{3.3}$$

describes density variations caused by variations in temperature T, pressure p, and composition ξ . The latter contribution needs to be considered for describing the effects of light elements released from a growing solid iron core in a so-called double diffusive approach.

To close the system we also have to formulate the dynamic changes of entropy, pressure, and composition. The evolution equation for pressure can be derived from the Navier-Stokes equation, as will be further discussed below. For entropy variations we use the so-called energy or heat equation

$$\rho T \left(\frac{\partial s}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} s \right) = \boldsymbol{\nabla} \cdot (k \boldsymbol{\nabla} T) + \boldsymbol{\Phi}_{\nu} + \lambda \mu_0 \left(\boldsymbol{\nabla} \times \boldsymbol{B} \right)^2 + \epsilon, \tag{3.4}$$

where Φ_{ν} corresponds to the viscous heating expressed by

$$\Phi_{\nu} = 2\rho \left[e_{ij}e_{ji} - \frac{1}{3} \left(\boldsymbol{\nabla} \cdot \boldsymbol{u} \right)^{2} \right]$$

Note that we use here the summation convention over the indices i and j. The second last term on the right hand side is the Ohmic heating due to electric currents. The last term is a volumetric sink or source term that can describe various effects, for example radiogenic heating, the mixing-in of the light elements or, when radially dependent, potential variations in the adiabatic gradient (see below). For chemical composition, we finally use

$$\rho\left(\frac{\partial \xi}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \xi\right) = \boldsymbol{\nabla} \cdot (k_{\xi} \boldsymbol{\nabla} \xi) + \epsilon_{\xi}, \tag{3.5}$$

The induction equation is obtained from the Maxwell equations (ignoring displacement current) and Ohm's law (neglecting Hall effect):

$$\frac{\partial \boldsymbol{B}}{\partial t} = \boldsymbol{\nabla} \times (\boldsymbol{u} \times \boldsymbol{B} - \lambda \boldsymbol{\nabla} \times \boldsymbol{B}). \tag{3.6}$$

When the magnetic diffusivity λ is homogeneous this simplifies to the commonly used form

$$\frac{\partial \boldsymbol{B}}{\partial t} = \boldsymbol{\nabla} \times (\boldsymbol{u} \times \boldsymbol{B}) + \lambda \, \Delta \boldsymbol{B}. \tag{3.7}$$

The physical properties determining above equations are rotation rate Ω , the kinematic viscosity ν , the magnetic permeability μ_0 , gravity g, thermal conductivity k, Fick's conductivity k_{ξ} , magnetic diffusivity λ . The latter connects to the electrical conductivity σ via $\lambda = 1/(\mu_0 \sigma)$. The thermodynamics properties appearing in (3.3) are the thermal expansivity at constant pressure (and composition)

$$\alpha = -\frac{1}{\rho} \left(\frac{\partial \rho}{\partial T} \right)_{p,\xi},\tag{3.8}$$

the compressibility at constant temperature

$$\beta = \frac{1}{\rho} \left(\frac{\partial \rho}{\partial p} \right)_{T,\xi}$$

and an equivalent parameter δ for the dependence of density on composition:

$$\delta = -\frac{1}{\rho} \left(\frac{\partial \rho}{\partial \xi} \right)_{p,T},\tag{3.9}$$

3.1 The reference state

The convective flow and the related processes including magnetic field generation constitute only small disturbances around a background or reference state. In the following we denote the background state with a tilde and the disturbance we are interested in with a prime. Formally we will solve equations in first order of a smallness parameters ϵ which quantified the ratio of convective disturbances to background state:




Fig. 3.1: Sketch of the spherical shell model and its system of coordinate.

$$\epsilon \sim \frac{T'}{\tilde{T}} \sim \frac{p'}{\tilde{p}} \sim \frac{\rho'}{\tilde{\rho}} \sim \dots \ll 1.$$
 (3.10)

The background state is hydrostatic, i.e. obeys the simple force balance

$$\nabla \tilde{p} = \tilde{\rho} \tilde{\boldsymbol{g}}. \tag{3.11}$$

Convective motions are supposed to be strong enough to provide homogeneous entropy (and composition). The reference state is thus adiabatic and its gradients can be expressed in terms of the pressure gradient (3.11):

$$\frac{\nabla \tilde{T}}{\tilde{T}} = \frac{1}{\tilde{T}} \left(\frac{\partial T}{\partial p} \right)_s \nabla p = \frac{\alpha}{c_p} \tilde{\mathbf{g}}, \tag{3.12}$$

$$\frac{\nabla \tilde{\rho}}{\tilde{\rho}} = \frac{1}{\tilde{\rho}} \left(\frac{\partial \rho}{\partial p} \right)_{s} \nabla p = \beta \tilde{\rho} \tilde{\boldsymbol{g}}. \tag{3.13}$$

The reference state obviously dependence only on radius. Dimensionless numbers quantifying the temperature and density gradients are called dissipation number Di and compressibility parameter Co respectively:

$$Di = \frac{\alpha d}{c_p} \tilde{g},$$

and

$$Co = d\beta \tilde{\rho} \tilde{g}.$$

3.1. The reference state

Here d is a typical length scale, for example the shell thickness of the problem. The dissipation number is something like an inverse temperature scale hight while the compressibility parameters is an inverse density scale hight. The ratio of both numbers also helps to quantify the relative impact of temperature and pressure on density variations:

$$\frac{\alpha \nabla T}{\beta \nabla \rho} \approx \alpha \tilde{T} \frac{Di}{Co}.$$
(3.14)

As an example we demonstrate how to derive the first order continuity equation here. Using $\rho = \tilde{\rho} + \rho'$ in (3.2) leads to

$$\frac{\partial \tilde{\rho}}{\partial t} + \frac{\partial \rho'}{\partial t} = -\boldsymbol{\nabla} \cdot (\tilde{\rho}\boldsymbol{u}) - \boldsymbol{\nabla} \cdot (\rho'\boldsymbol{u}).$$

The zero order term vanishes since the background density is considered static (or actually changing very slowly on very long time scales). The second term in the right hand side is obviously of second order. The ratio of the remaining two terms can be estimated to also be of first order in ϵ , meaning that the time derivative of ρ is actually also of second order:

$$\frac{[\partial \rho/\partial t]}{[\boldsymbol{\nabla} \cdot \rho \boldsymbol{u}]} \approx \frac{\rho'}{\tilde{\rho}} \approx \epsilon .$$

Square brackets denote order of magnitude estimates here. We have used the fact that the reference state is static and assume time scale of changes are comparable (or slower) ρ' than the time scales represented by u and that length scales associated to the gradient operator are not too small. We can then neglect local variations in ρ' which means that sound waves are filtered out. This first order continuity equation thus simply reads:

$$\nabla \cdot (\tilde{\rho} \boldsymbol{u}) = 0. \tag{3.15}$$

This defines the so-called anelastic approximation where sound waves are filtered out by neglecting the local time derivative of density. This approximation is justified when typical velocities are sufficiently smaller than the speed of sound.

3.2 Boussinesq approximation

For Earth the dissipation number and the compressibility parameter are around 0.2 when temperature and density jump over the whole liquid core are considered. This motivates the so called Boussinesq approximation where Di and Co are assumed to vanish. The continuity equation (3.2) then simplifies further:

$$\frac{1}{\tilde{\rho}} \nabla \cdot \tilde{\rho} \boldsymbol{u} = \frac{\boldsymbol{u}}{\tilde{\rho}} \cdot \nabla \tilde{\rho} + \nabla \cdot \boldsymbol{u} \approx \nabla \cdot \boldsymbol{u} = 0.$$

When using typical number for Earth, (3.14) becomes 0.05 so that pressure effects on density may be neglected. The first order Navier-Stokes equation (after to zero order hydrostatic reference solution has been subtracted) then reads:

$$\tilde{\rho}\left(\frac{\partial \boldsymbol{u}}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \boldsymbol{u}\right) = -\boldsymbol{\nabla} p' - 2\rho \boldsymbol{\Omega} \times \boldsymbol{u} + \alpha \tilde{g}_o T' \frac{\boldsymbol{r}}{r_o} + \delta \tilde{g}_o \xi' \frac{\boldsymbol{r}}{r_o} + \frac{1}{\mu_0} (\boldsymbol{\nabla} \times \boldsymbol{B}) \times \boldsymbol{B} + \tilde{\rho} \nu \Delta \boldsymbol{u}. \tag{3.16}$$

Here u and B are understood as first order disturbances and p' is the first order non-hydrostatic pressure and T' the super-adiabatic temperature and ξ the super-adiabatic chemical composition. Above we have adopted a simplification of the buoyancy term. In the Boussinesq limit with vanishing Co and a small density difference between a solid inner and a liquid outer core a linear gravity dependence provides a reasonable approximation:

$$\tilde{\boldsymbol{g}} = \tilde{g}_o \frac{\boldsymbol{r}}{r_o},$$

where we have chosen the gravity \tilde{g}_o at the outer boundary radius r_o as reference.

The first order energy equation becomes

$$\tilde{\rho}\left(\frac{\partial T'}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} T'\right) = \kappa \Delta T' + \epsilon, \tag{3.17}$$

where we have assumed a homogeneous k and neglected viscous and Ohmic heating which can be shown to scale with Di as we discuss below. Furthermore, we have used the simple relation

$$\partial s \approx \frac{\tilde{\rho}c_p}{\tilde{T}}\partial T,$$

defined the thermal diffusivity

$$\kappa = \frac{k}{\tilde{\rho}c_p},$$

and adjusted the definition of ϵ . Finally the first order equation for chemical composition becomes

$$\tilde{\rho}\left(\frac{\partial \xi'}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \xi'\right) = \kappa_{\xi} \Delta \xi' + \epsilon_{\xi},\tag{3.18}$$

where we have assumed a homogeneous k_{ξ} and adjusted the definition of ϵ_{ξ} .

MagIC solves a dimensionless form of the differential equations. Time is scaled in units of the viscous diffusion time d^2/ν , length in units of the shell thickness d, temperature in units of the temperature drop $\Delta T = T_o - T_i$ over the shell, composition in units of the composition drop $\Delta \xi = \xi_o - \xi_i$ over the shell and magnetic field in units $(\mu \lambda \tilde{\rho} \Omega)^{1/2}$. Technically the transition to the dimensionless form is achieved by the substitution

$$r \to r \ d, \quad t \to (d^2/\nu) \ t, \quad T \to \Delta T \ T, \quad \xi \to \Delta \xi \ \xi, \quad B \to (\mu \lambda \tilde{\rho} \Omega)^{1/2} \ B$$

where r stands for any length. The next step then is to collect the physical properties as a few possible characteristic dimensionless numbers. Note that many different scalings and combinations of dimensionless numbers are possible. For the Navier-Stokes equation in the Boussinesq limit MagIC uses the form:

$$\left(\frac{\partial \boldsymbol{u}}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \,\boldsymbol{u}\right) = -\boldsymbol{\nabla} p' - \frac{2}{E} \boldsymbol{e}_{\boldsymbol{z}} \times \boldsymbol{u} + \frac{Ra}{Pr} T' \frac{\boldsymbol{r}}{r_o} + \frac{Ra_{\xi}}{Sc} \xi' \frac{\boldsymbol{r}}{r_o} + \frac{1}{EPm} (\boldsymbol{\nabla} \times \boldsymbol{B}) \times \boldsymbol{B} + \Delta \boldsymbol{u}, \quad (3.19)$$

where e_z is the unit vector in the direction of the rotation axis and the meaning of the pressure disturbance p' has been adjusted to the new dimensionless equation form.

3.3 Anelastic approximation

The anelastic approximation adopts the simplified continuity (3.15). The background state can be specified in different ways, for example by providing profiles based on internal models and/or ab initio simulations. We will assume a polytropic ideal gas in the following.

3.3.1 Analytical solution in the limit of an ideal gas

In the limit of an ideal gas which follows $\tilde{p} = \tilde{\rho}\tilde{T}$ and has $\alpha = 1/\tilde{T}$, one directly gets:

$$\frac{d\tilde{T}}{dr} = -Di\,\tilde{g}(r),$$
$$\tilde{\rho} = \tilde{T}^{1/(\gamma - 1)},$$

where $\gamma = c_p/c_v$. Note that we have moved to a dimensionless formulations here, where all quantities have been normalized with their outer boundary values and Di refers to the respective outer boundary value. If we in addition make the assumption of a centrally-condensed mass in the center of the spherical shell of radius $r \in [r_i, r_o]$, i.e. $g \propto 1/r^2$, this leads to

$$\begin{split} \tilde{T}(r) &= Di \frac{r_o^2}{r} + (1 - Di \, r_o), \\ \tilde{\rho}(r) &= \tilde{T}^m, \\ Di &= \frac{r_i}{r_o} \left(\exp \frac{N_\rho}{m} - 1 \right), \end{split}$$

where $N_{\rho} = \ln(\tilde{\rho}_i/\tilde{\rho}_o)$ is the number of density scale heights of the reference state and $m = 1/(\gamma - 1)$ is the polytropic index.

Warning:

- The relationship between N_{ρ} and the dissipation number Di directly depends on the gravity profile. The formula above is only valid when $g \propto 1/r^2$.
- In this formulation, when you change the polytropic index m, you also change the nature of the fluid you're modelling since you accordingly modify $\gamma = c_n/c_v$.

3.3.2 Anelastic MHD equations

In the most general formulation, all physical properties defining the background state may vary with depth. Specific reference values must then be chosen to provide a unique dimensionless formulations and we typically chose outer boundary values here. The exception is the magnetic diffusivity where we adopt the inner boundary value instead. The motivation is twofold: (i) it allows an easier control of the possible continuous conductivity value in the inner core; (ii) it is a more natural choice when modelling gas giants planets which exhibit a strong electrical conductivity decay in the outer layer.

The time scale is then the viscous diffusion time d^2/ν_o where ν_o is the kinematic viscosity at the outer boundary. Magnetic field is expressed in units of $(\rho_o \mu_0 \lambda_i \Omega)^{1/2}$, where ρ_o is the density at the outer boundary and λ_i is the magnetic diffusivity at the **inner** boundary.

This leads to the following sets of dimensionless equations:

$$\left(\frac{\partial \boldsymbol{u}}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \boldsymbol{u}\right) = -\boldsymbol{\nabla} \left(\frac{p'}{\tilde{\rho}}\right) - \frac{2}{E} \boldsymbol{e}_{\boldsymbol{z}} \times \boldsymbol{u} + \frac{Ra}{Pr} \tilde{g} \, s' \, \boldsymbol{e}_{\boldsymbol{r}} + \frac{Ra_{\boldsymbol{\xi}}}{Sc} \tilde{g} \, \xi' \, \boldsymbol{e}_{\boldsymbol{r}} + \frac{1}{Pm \, E \, \tilde{\rho}} \left(\boldsymbol{\nabla} \times \boldsymbol{B}\right) \times \boldsymbol{B} + \frac{1}{\tilde{\rho}} \boldsymbol{\nabla} \cdot \boldsymbol{S}, \tag{3.20}$$

$$\nabla \cdot \tilde{\rho} \boldsymbol{u} = 0, \tag{3.21}$$

$$\nabla \cdot \boldsymbol{B} = 0, \tag{3.22}$$

$$\tilde{\rho} \left(\frac{\partial \xi'}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \xi' \right) = \frac{1}{Sc} \boldsymbol{\nabla} \cdot (\kappa_{\xi}(r) \tilde{\rho} \boldsymbol{\nabla} \xi')$$
(3.23)

$$\frac{\partial \boldsymbol{B}}{\partial t} = \boldsymbol{\nabla} \times (\boldsymbol{u} \times \boldsymbol{B}) - \frac{1}{Pm} \boldsymbol{\nabla} \times (\lambda(r) \boldsymbol{\nabla} \times \boldsymbol{B}). \tag{3.24}$$

Here \tilde{g} and $\tilde{\rho}$ are the normalized radial gravity and density profiles that reach one at the outer boundary.

3.3.3 Entropy equation and turbulent diffusion

The entropy equation usually requires an additional assumption in most of the existing anelastic approximations. Indeed, if one simply expands Eq. (3.4) with the classical temperature diffusion an operator of the form:

$$\epsilon \nabla \cdot (K \nabla T') + \nabla \cdot (K \nabla \tilde{T}),$$

will remain the right-hand side of the equation. At first glance, there seems to be a $1/\epsilon$ factor between the first term and the second one, which would suggest to keep only the second term in this expansion. However, for astrophysical objects which exhibit strong convective driving (and hence large Rayleigh numbers), the diffusion of the adiabatic background is actually very small and may be comparable or even smaller in magnitude than the ϵ terms representing the usual convective perturbations. For the Earth core for instance, if one assumes that the typical temperature fluctuations are of the order of 1 mK and the temperature contrast between the inner and outer core is of the order of 1000 K, then $\epsilon \sim 10^{-6}$. The ratio of the two terms can thus be estimated as

$$\epsilon \frac{T'/\delta^2}{T/d^2},\tag{3.25}$$

where d is the thickness of the inner core and δ is the typical thermal boundary layer thickness. This ratio is exactly one when $\delta = 1$ m, a plausible value for the Earth inner core.

In numerical simulations however, the over-estimated diffusivities restrict the computational capabilities to much lower Rayleigh numbers. As a consequence, the actual boundary layers in a global DNS will be much thicker and the ratio (3.25) will be much smaller than unity. The second terms will thus effectively acts as a radial-dependent heat source or sink that will drive or hinder convection. This is one of the physical motivation to rather introduce a **turbulent diffusivity** that will be approximated by

$$\kappa \tilde{\rho} \tilde{T} \nabla s$$
,

where κ is the turbulent diffusivity. Entropy diffusion is assumed to dominate over temperature diffusion in turbulent flows.

The choice of the entropy scale to non-dimensionalize Eq. (3.4) also depends on the nature of the boundary conditions: it can be simply the entropy contrast over the layer Δs when the entropy is held constant at both boundaries, or d(ds/dr) when flux-based boundary conditions are employed. We will restrict to the first option in the following, but keep in mind that depending on your setup, the entropy reference scale (and thus the Rayleigh number definition) might change.

$$\tilde{\rho}\tilde{T}\left(\frac{\partial s'}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla}s'\right) = \frac{1}{Pr}\boldsymbol{\nabla}\cdot\left(\kappa(r)\tilde{\rho}\tilde{T}\boldsymbol{\nabla}s'\right) + \frac{Pr\,Di}{Ra}\boldsymbol{\Phi}_{\nu} + \frac{Pr\,Di}{Pm^2\,E\,Ra}\lambda(r)\left(\boldsymbol{\nabla}\times\boldsymbol{B}\right)^2,\tag{3.26}$$

A comparison with (3.20) reveals meaning of the different non-dimensional numbers that scale viscous and Ohmic heating. The fraction Pr/Ra simply expresses the ratio of entropy and flow in the Navier-Stokes equation, while the additional factor 1/EPm reflects the scale difference of magnetic field and flow. Then remaining dissipation number Di then expresses the relative importance of viscous and Ohmic heating compared to buoyancy and Lorentz force in the Navier-Stokes equation. For small Di both heating terms can be neglected compared to entropy changes due to advection, an limit that is used in the Boussinesq approximation.

3.4 Dimensionless control parameters

The equations (3.20)-(3.26) are governed by four dimensionless numbers: the Ekman number

$$E = \frac{\nu}{\Omega d^2},\tag{3.27}$$

the thermal Rayleigh number

$$Ra = \frac{\alpha_o g_o T_o d^3 \Delta s}{c_p \kappa_o \nu_o},\tag{3.28}$$

the compositional Rayleigh number

$$Ra_{\xi} = \frac{\delta_o g_o d^3 \Delta \xi}{\kappa_{\xi} \nu_o},\tag{3.29}$$

the Prandtl number

$$Pr = \frac{\nu_o}{\kappa_o},\tag{3.30}$$

the Schmidt number

$$Sc = \frac{\nu_o}{\kappa_{\xi}},\tag{3.31}$$

and the magnetic Prandtl number

$$Pm = \frac{\nu_o}{\lambda_i}. (3.32)$$

In addition to these four numbers, the reference state is controlled by the geometry of the spherical shell given by its radius ratio

$$\eta = \frac{r_i}{r_c},\tag{3.33}$$

and the background density and temperature profiles, either controlled by Di or by N_{ρ} and m.

In the Boussinesq approximation all physical properties are assumed to be homogeneous and we can drop the subindices o and i except for gravity. Moreover, the Rayleigh number can be expressed in terms of the temperature jump across the shell:

$$Ra = \frac{\alpha g_o d^3 \Delta T}{\kappa \nu}. (3.34)$$

See also:

In MagIC, those control parameters can be adjusted in the &phys_param section of the input namelist.

Variants of the non-dimensional equations and control parameters result from different choices for the fundamental scales. For the length scale often r_o is chosen instead of d. Other natural scales for time are the magnetic or the thermal diffusion time, or the rotation period. There are also different options for scaling the magnetic field strength. The prefactor of two, which is retained in the Coriolis term in (3.20), is often incorporated into the definition of the Ekman number.

See also:

Those references timescales and length scales can be adjusted by several input parameters in the &control section of the input namelist.

3.4.1 Usual diagnostic quantities

Characteristic properties of the solution are usually expressed in terms of non-dimensional diagnostic parameters. In the context of the geodynamo for instance, the two most important ones are the magnetic Reynolds number Rm and the Elsasser number Λ . Usually the rms-values of the velocity u_{rms} and of the magnetic field B_{rms} inside the spherical shell are taken as characteristic values. The magnetic Reynolds number

$$Rm = \frac{u_{rms}d}{\lambda_i}$$

can be considered as a measure for the flow velocity and describes the ratio of advection of the magnetic field to magnetic diffusion. Other characteristic non-dimensional numbers related to the flow velocity are the (hydrodynamic) Reynolds number

$$Re = \frac{u_{rms}d}{\nu_o},$$

which measures the ratio of inertial forces to viscous forces, and the Rossby number

$$Ro = \frac{u_{rms}}{\Omega d},$$

a measure for the ratio of inertial to Coriolis forces.

$$\Lambda = \frac{B_{rms}^2}{\mu_0 \lambda_i \rho_o \Omega}$$

measures the ratio of Lorentz to Coriolis forces and is equivalent to the square of the non-dimensional magnetic field strength in the scaling chosen here.

See also:

The time-evolution of these diagnostic quantities are stored in the par.TAG file produced during the run of MagIC.

3.5 Boundary conditions and treatment of inner core

3.5.1 Mechanical conditions

In its simplest form, when modelling the geodynamo, the fluid shell is treated as a container with rigid, impenetrable, and co-rotating walls. This implies that within the rotating frame of reference all velocity components vanish at r_o and

 r_i . In case of modelling the free surface of a gas giant planets or a star, it is preferable to rather replace the condition of zero horizontal velocity by one of vanishing viscous shear stresses (the so-called free-slip condition).

Furthermore, even in case of modelling the liquid iron core of a terrestrial planet, there is no a priori reason why the inner core should necessarily co-rotate with the mantle. Some models for instance allow for differential rotation of the inner core and mantle with respect to the reference frame. The change of rotation rate is determined from the net torque. Viscous, electromagnetic, and torques due to gravitational coupling between density heterogeneities in the mantle and in the inner core contribute.

See also:

The mechanical boundary conditions can be adjusted with the parameters *ktopv* and *kbotv* in the *&phys_param* section of the input namelist.

3.5.2 Magnetic boundary conditions and inner core conductivity

When assuming that the fluid shell is surrounded by electrically insulating regions (inner core and external part), the magnetic field inside the fluid shell matches continuously to a potential field in both the exterior and the interior regions. Alternative magnetic boundary conditions (like cancellation of the horizontal component of the field) are also possible.

Depending on the physical problem you want to model, treating the inner core as an insulator is not realistic either, and it might instead be more appropriate to assume that it has the same electrical conductivity as the fluid shell. In this case, an equation equivalent to (3.24) must be solved for the inner core, where the velocity field simply describes the solid body rotation of the inner core with respect to the reference frame. At the inner core boundary a continuity condition for the magnetic field and the horizontal component of the electrical field apply.

See also:

The magnetic boundary conditions can be adjusted with the parameters *ktopb* and *kbotb* in the *&phys_param* section of the input namelist.

3.5.3 Thermal boundary conditions and distribution of buoyancy sources

In many dynamo models, convection is simply driven by an imposed fixed super-adiabatic entropy contrast between the inner and outer boundaries. This approximation is however not necessarily the best choice, since for instance, in the present Earth, convection is thought to be driven by a combination of thermal and compositional buoyancy. Sources of heat are the release of latent heat of inner core solidification and the secular cooling of the outer and inner core, which can effectively be treated like a heat source. The heat loss from the core is controlled by the convecting mantle, which effectively imposes a condition of fixed heat flux at the core-mantle boundary on the dynamo. The heat flux is in that case spatially and temporally variable.

See also:

The thermal boundary conditions can be adjusted with the parameters *ktops* and *kbots* in the *&phys_param* section of the input namelist.

3.5.4 Chemical composition boundary conditions

They are treated in a very similar manner as the thermal boundary conditions

See also:

The boundary conditions for composition can be adjusted with the parameters *ktopxi* and *kbotxi* in the *&phys_param* section of the input namelist.

CHAPTER

FOUR

NUMERICAL TECHNIQUE

MagIC is a pseudo-spectral MHD code. This numerical technique was originally developed by P. Gilman and G. Glatzmaier for the spherical geometry. In this approach the unknowns are expanded into complete sets of functions in radial and angular directions: Chebyshev polynomials or Finite differences in the radial direction and spherical harmonic functions in the azimuthal and latitudinal directions. This allows to express all partial derivatives analytically. Employing orthogonality relations of spherical harmonic functions and using collocation in radius then lead to algebraic equations that are integrated in time with a mixed implicit/explicit time stepping scheme. The nonlinear terms and the Coriolis force are evaluated in the physical (or grid) space rather than in spectral space. Although this approach requires costly numerical transformations between the two representations (from spatial to spectral using Legendre and Fourier transforms), the resulting decoupling of all spherical harmonic modes leads to a net gain in computational speed. Before explaining these methods in more detail, we introduce the poloidal/toroidal decomposition.

4.1 Poloidal/toroidal decomposition

Any vector v that fulfills $\nabla \cdot v = 0$, i.e. a so-called *solenoidal field*, can be decomposed in a poloidal and a toroidal part W and Z, respectively

$$v = \nabla \times (\nabla \times W e_r) + \nabla \times Z e_r.$$

Three unknown vector components are thus replaced by two scalar fields, the poloidal potential W and the toroidal potential Z. This decomposition is unique, aside from an arbitrary radial function f(r) that can be added to W or Z without affecting v.

In the anelastic approximation, such a decomposition can be used for the mass flux $\tilde{\rho}u$ and the magnetic field B. This yields

$$\tilde{\rho} \boldsymbol{u} = \boldsymbol{\nabla} \times (\boldsymbol{\nabla} \times W \, \boldsymbol{e_r}) + \boldsymbol{\nabla} \times Z \, \boldsymbol{e_r},
\boldsymbol{B} = \boldsymbol{\nabla} \times (\boldsymbol{\nabla} \times g \, \boldsymbol{e_r}) + \boldsymbol{\nabla} \times h \, \boldsymbol{e_r}.$$
(4.1)

The two scalar potentials of a divergence free vector field can be extracted from its radial component and the radial component of its curl using the fact that the toroidal field has not radial component:

$$e_{r} \cdot \tilde{\rho} u = -\Delta_{H} W,$$

$$e_{r} \cdot (\nabla \times u) = -\Delta_{H} Z,$$
(4.2)

where the operator Δ_H denotes the horizontal part of the Laplacian:

$$\Delta_H = \frac{1}{r^2 \sin \theta} \frac{\partial}{\partial \theta} \left(\sin \theta \frac{\partial}{\partial \theta} \right) + \frac{1}{r^2 \sin^2 \theta} \frac{\partial^2}{\partial^2 \phi}.$$
 (4.3)

The equation (4.1) can be expanded in spherical coordinates. The three components of $\tilde{\rho}u$ are given by

$$\tilde{\rho} \boldsymbol{u} = -(\Delta_H W) \, \boldsymbol{e}_{\boldsymbol{r}} + \left(\frac{1}{r} \frac{\partial W}{\partial \theta} + \frac{1}{r \sin \theta} \frac{\partial Z}{\partial \phi} \right) \, \boldsymbol{e}_{\boldsymbol{\theta}} + \left(\frac{1}{r \sin \theta} \frac{\partial W}{\partial \phi} - \frac{1}{r} \frac{\partial Z}{\partial \theta} \right) \, \boldsymbol{e}_{\boldsymbol{\phi}},\tag{4.4}$$

while the curl of $\tilde{\rho}u$ is expressed by

$$\nabla \times \tilde{\rho} \boldsymbol{u} = -\left(\Delta_{H} Z\right) \boldsymbol{e}_{\boldsymbol{r}} + \left[-\frac{1}{r \sin \theta} \frac{\partial}{\partial \phi} \left(\frac{\partial^{2}}{\partial r^{2}} + \Delta_{H} \right) W + \frac{1}{r} \frac{\partial^{2} Z}{\partial r \partial \theta} \right] \boldsymbol{e}_{\boldsymbol{\theta}} + \left[\frac{1}{r} \frac{\partial}{\partial \theta} \left(\frac{\partial^{2}}{\partial r^{2}} + \Delta_{H} \right) W + \frac{1}{r \sin \theta} \frac{\partial^{2} Z}{\partial r \partial \phi} \right] \boldsymbol{e}_{\boldsymbol{\phi}},$$

$$(4.5)$$

Using the horizontal part of the divergence operator

$$\nabla_H = \frac{1}{r \sin \theta} \frac{\partial}{\partial \theta} \sin \theta \ e_{\theta} + \frac{1}{r \sin \theta} \frac{\partial}{\partial \phi} \ e_{\phi}$$

above expressions can be simplified to

$$\tilde{\rho}\boldsymbol{u} = -\Delta_H \,\,\boldsymbol{e_r} \,\, W + \boldsymbol{\nabla}_H \frac{\partial}{\partial r} \,\, W + \boldsymbol{\nabla}_H \times \boldsymbol{e_r} \,\, Z$$

and

$$\nabla \times \tilde{\rho} \boldsymbol{u} = -\Delta_H \, \boldsymbol{e}_r \, Z + \boldsymbol{\nabla}_H \frac{\partial}{\partial r} \, Z - \boldsymbol{\nabla}_H \times \Delta_H \boldsymbol{e}_r \, W \ .$$

Below we will use the fact that the horizontal components of the poloidal field depend on the radial derivative of the poloidal potential.

4.2 Spherical harmonic representation

Spherical harmonic functions Y_{ℓ}^m are a natural choice for the horizontal expansion in colatitude θ and longitude ϕ :

$$Y_{\ell}^{m}(\theta,\phi) = P_{\ell}^{m}(\cos\theta) e^{im\phi},$$

where ℓ and m denote spherical harmonic degree and order, respectively, P_{ℓ}^{m} is an associated Legendre function. Different normalization are in use. Here we adopt a complete normalization so that the orthogonality relation reads

$$\int_{0}^{2\pi} d\phi \int_{0}^{\pi} \sin\theta \, d\theta \, Y_{\ell}^{m}(\theta,\phi) \, Y_{\ell'}^{m'}(\theta,\phi) = \delta_{\ell\ell'} \delta^{mm'}. \tag{4.6}$$

This means that

$$Y_{\ell}^{m}(\theta,\phi) = \left(\frac{(2\ell+1)}{4\pi} \frac{(\ell-|m|)!}{(\ell+|m|)!}\right)^{1/2} P_{\ell}^{m}(\cos\theta) e^{im\phi},$$

As an example, the spherical harmonic representation of the magnetic poloidal potential $g(r, \theta, \phi)$, truncated at degree and order ℓ_{max} , then reads

$$g(r, \theta, \phi) = \sum_{\ell=0}^{\ell_{max}} \sum_{m=-\ell}^{\ell} g_{\ell m}(r) Y_{\ell}^{m}(\theta, \phi),$$
(4.7)

with

$$g_{\ell m}(r) = \frac{1}{\pi} \int_0^{\pi} d\theta \sin\theta \ g_m(r,\theta) \ P_{\ell}^m(\cos\theta), \tag{4.8}$$

$$g_m(r,\theta) = \frac{1}{2\pi} \int_0^{2\pi} d\phi \ g(r,\theta,\phi) \ e^{-im\phi}.$$
 (4.9)

The potential $g(r, \theta, \phi)$ is a real function so that $g_{\ell m}^{\star}(r) = g_{\ell, -m}(r)$, where the asterisk denotes the complex conjugate. Thus, only coefficients with $m \geq 0$ have to be considered. The same kind of expansion is made for the toroidal magnetic potential, the mass flux potentials, pressure, entropy (or temperature) and chemical composition.

The equations (4.8) and (4.9) define a two-step transform from the longitude/latitude representation to the spherical harmonic representation $(r, \theta, \phi) \longrightarrow (r, \ell, m)$. The equation (4.7) formulates the inverse procedure $(r, \ell, m) \longrightarrow (r, \theta, \phi)$. Fast-Fourier transforms are employed in the longitudinal direction, requiring (at least) $N_{\phi} = 2\ell_{max} + 1$ evenly spaced grid points ϕ_i . MagIC relies on the Gauss-Legendre quadrature for evaluating the integral (4.8)

$$g_{\ell m}(r) = \frac{1}{N_{\theta}} \sum_{j=1}^{N_{\theta}} w_j g_m(r, \theta_j) P_{\ell}^m(\cos \theta_j),$$

where θ_j are the N_{θ} Gaussian quadrature points defining the latitudinal grid, and w_j are the respective weights. Prestored values of the associated Legendre functions at grid points θ_j in combination with a FFT in ϕ provide the inverse transform (4.7). Generally, $N_{\phi} = 2N_{\theta}$ is chosen, which provides isotropic resolution in the equatorial region. Choosing $\ell_{max} = [\min(2N_{\theta}, N_{\phi}) - 1]/3$ prevents aliasing errors.

See also:

In MagIC, the Legendre functions are defined in the subroutine plm_theta. The Legendre transforms from spectral to grid space are computed in the module legendre_spec_to_grid, while the backward transform (from grid space to spectral space) are computed in the module legendre_grid_to_spec. The fast Fourier transforms are computed in the module fft.

4.2.1 Special recurrence relations

The action of a horizontal Laplacian (4.3) on spherical harmonics can be analytically expressed by

$$\Delta_H Y_\ell^m = -\frac{\ell(\ell+1)}{r^2} Y_\ell^m \,. \tag{4.10}$$

They are several useful recurrence relations for the Legendre polynomials that will be further employed to compute Coriolis forces and the θ and ϕ derivatives of advection and Lorentz forces. Four of these operators are used in **MagIC**. The first one is defined by

$$\vartheta_1 = \frac{1}{\sin \theta} \frac{\partial}{\partial \theta} \sin^2 \theta = \sin \theta \frac{\partial}{\partial \theta} + 2\cos \theta.$$

The action of this operator on a Legendre polynomials is given by

$$\vartheta_1 = (\ell + 2) c_{\ell+1}^m P_{\ell+1}^m (\cos \theta) - (\ell - 1) c_{\ell}^m P_{\ell-1}^m (\cos \theta),$$

where c_{ℓ}^{m} is defined by

$$c_{\ell}^{m} = \sqrt{\frac{(\ell+m)(\ell-m)}{(2\ell-1)(2\ell+1)}}.$$
(4.11)

How is that implemented in the code? Let's assume we want the spherical harmonic contribution of degree ℓ and order m for the expression

$$\frac{1}{\sin \theta} \frac{\partial}{\partial \theta} (\sin \theta f(\theta)).$$

In order to employ the operator ϑ_1 for the derivative, we thus define a new function

$$F(\theta) = f(\theta) / \sin \theta$$
,

so that

$$\frac{1}{\sin \theta} \frac{\partial}{\partial \theta} [\sin \theta f(\theta)] = \vartheta_1 F(\theta).$$

Expanding $F(\theta)$ in Legendre polynomials and using the respective orthogonality relation we can then map out the required contribution in the following way:

$$\left| \int_0^{\pi} d\theta \sin \theta \, P_{\ell}^m \vartheta_1 \sum_{\ell'} F_{\ell'}^m P_{\ell'}^m = (\ell+1) \, c_{\ell}^m \, F_{\ell-1}^m - \ell \, c_{\ell+1}^m \, F_{\ell+1}^m \, . \right| \tag{4.12}$$

Here, we have assumed that the Legendre functions are completely normalized such that

$$\int_0^{\pi} d\theta \sin \theta \, P_{\ell}^m P_{\ell'}^m = \delta_{\ell\ell'} \,.$$

See also:

This operator is defined in the module horizontal_data by the variables dTheta1S for the first part of the right-hand side of (4.12) and dTheta1A for the second part.

The second operator used to formulate colatitude derivatives is

$$\vartheta_2 = \sin \theta \frac{\partial}{\partial \theta} \,.$$

The action of this operator on the Legendre polynomials reads

$$\vartheta_2 P_{\ell}^m(\cos \theta) = \ell c_{\ell+1}^m P_{\ell+1}^m(\cos \theta) - (\ell+1) c_{\ell}^m P_{\ell-1}^m(\cos \theta),$$

so that

$$\int_0^{\pi} d\theta \sin \theta \, P_{\ell}^m \vartheta_2 \sum_{\ell'} f_{\ell'}^m P_{\ell'}^m = (\ell - 1) \, c_{\ell}^m \, f_{\ell-1}^m - (\ell + 2) \, c_{\ell+1}^m \, f_{\ell+1}^m \,. \tag{4.13}$$

See also:

This operator is defined in the module horizontal_data by the variables dTheta2S for the first part of the right-hand side of (4.13) and dTheta2A for the second part.

The third combined operator is defined by:

$$\vartheta_3 = \sin \theta \frac{\partial}{\partial \theta} + \cos \theta \, L_H \,,$$

where $-L_H/r^2 = \Delta_H$.

Acting with ϑ_3 on a Legendre function gives:

$$\vartheta_3 P_{\ell}^m(\cos \theta) = \ell(\ell+1) c_{\ell+1}^m P_{\ell+1}^m(\cos \theta) + (\ell-1)(\ell+1) c_{\ell}^m P_{\ell-1}^m(\cos \theta),$$

which results into:

$$\int_0^\pi d\theta \sin\theta \, P_\ell^m \vartheta_3 \sum_{\ell'} f_{\ell'}^m P_{\ell'}^m = (\ell - 1)(\ell + 1) \, c_\ell^m \, f_{\ell-1}^m + \ell(\ell + 2) \, c_{\ell+1}^m \, f_{\ell+1}^m \,.$$
(4.14)

See also:

This operator is defined in the module $horizontal_data$ by the variables dTheta3S for the first part of the right-hand side of (4.14) and dTheta3A for the second part.

The fourth (and last) combined operator is defined by:

$$\vartheta_4 = \frac{1}{\sin \theta} \frac{\partial}{\partial \theta} \sin^2 \theta \, L_H = \vartheta 1 \, L_H \,,$$

Acting with ϑ_3 on a Legendre function gives:

$$\vartheta_4 P_{\ell}^m(\cos \theta) = \ell(\ell+1)(\ell+2) c_{\ell+1}^m P_{\ell+1}^m(\cos \theta) - \ell(\ell-1)(\ell+1) c_{\ell}^m P_{\ell-1}^m(\cos \theta),$$

which results into:

$$\int_0^{\pi} d\theta \, \sin\theta \, P_{\ell}^m \vartheta_4 \sum_{\ell'} f_{\ell'}^m P_{\ell'}^m = \ell(\ell-1)(\ell+1) \, c_{\ell}^m \, f_{\ell-1}^m - \ell(\ell+1)(\ell+2) \, c_{\ell+1}^m \, f_{\ell+1}^m \,.$$
(4.15)

See also:

This operator is defined in the module horizontal_data by the variables dTheta4S for the first part of the right-hand side of (4.15) and dTheta4A for the second part.

4.3 Radial representation

In MagIC, the radial dependencies are expanded into complete sets of functions: the Chebyshev polynomials C(x). The polynomial of degree n is defined by

$$C_n(x) = \cos [n \operatorname{arccos}(x)] - 1 \le x \le 1.$$

When truncating at degree N, the radial expansion of the poloidal magnetic potential reads

$$g_{\ell m}(r) = \sum_{n=0}^{N} g_{\ell m n} \, \mathcal{C}_n(r),$$
 (4.16)

with

$$g_{\ell mn} = \frac{2 - \delta_{n0}}{\pi} \int_{-1}^{1} \frac{dx \, g_{\ell m}(r(x)) \, \mathcal{C}_n(x)}{\sqrt{1 - x^2}}.$$
 (4.17)

The Chebyshev definition space $(-1 \le x \le 1)$ is then linearly mapped onto a radius range $(r_i \le r \le r_o)$ by

$$x(r) = 2\frac{r - r_i}{r_o - r_i} - 1. (4.18)$$

In addition, nonlinear mapping can be defined to modify the radial dependence of the grid-point density.

When choosing the N_r extrema of C_{N_r-1} as radial grid points,

$$x_k = \cos\left(\pi \frac{(k-1)}{N_r - 1}\right) , \quad k = 1, 2, \dots, N_r,$$
 (4.19)

the values of the Chebyshev polynomials at these points are simply given by the cosine functions:

$$C_{nk} = C_n(x_k) = \cos\left(\pi \frac{n(k-1)}{N_r - 1}\right).$$

This particular choice has two advantages. For one, the grid points become denser toward the inner and outer radius and better resolve potential thermal and viscous boundary layers. In addition, FFTs can be employed to switch between grid representation (4.16) and Chebyshev representations (4.17), rendering this procedure a fast-Chebyshev transform. Choosing $N_T > N$ provides radial dealiasing.

See also:

The Chebyshev (Gauss-Lobatto) grid is defined in the module <code>chebyshev_polynoms_mod</code>. The cosine transforms are computed in the modules <code>cosine_transform_even</code> and <code>fft_fac_mod</code>.

4.4 Spectral equations

We have now introduced the necessary tools for deriving the spectral equations. Taking the **radial components** of the Navier-Stokes equation and the induction equation provides the equations for the poloidal potentials $W(r, \theta, \phi)$ and $g(r, \theta, \phi)$. The **radial component of the curl** of these equations provides the equations for the toroidal counterparts $Z(r, \theta, \phi)$ and $h(r, \theta, \phi)$. The pressure remains an additional unknown. Hence one more equation involving $W_{\ell mn}$ and $p_{\ell mn}$ is required. It is obtained by taking the **horizontal divergence** of the Navier-Stokes equation.

Expanding all potentials in spherical harmonics and Chebyshev polynomials, multiplying with $Y_{\ell}^{m\star}$, and integrating over spherical surfaces (while making use of the orthogonality relation (4.6) results in equations for the coefficients $W_{\ell mn}$, $Z_{\ell mn}$, $g_{\ell mn}$, $h_{\ell mn}$, $P_{\ell mn}$ and $s_{\ell mn}$, respectively.

4.4.1 Equation for the poloidal potential W

The temporal evolution of W is obtained by taking e_r of each term entering the Navier-Stokes equation. For the time-derivative, one gets using (4.2):

$$\tilde{\rho} \boldsymbol{e_r} \cdot \left(\frac{\partial \boldsymbol{u}}{\partial t} \right) = \frac{\partial}{\partial t} (\boldsymbol{e_r} \cdot \tilde{\rho} \boldsymbol{u}) = -\Delta_H \frac{\partial W}{\partial t}.$$

For the viscosity term, one gets

$$\begin{split} \boldsymbol{e}_{r} \cdot \boldsymbol{\nabla} \cdot \boldsymbol{\mathsf{S}} &= -\nu \, \Delta_{H} \left[\frac{\partial^{2} W}{\partial r^{2}} + \left\{ 2 \frac{d \ln \nu}{dr} - \frac{1}{3} \frac{d \ln \tilde{\rho}}{dr} \right\} \frac{\partial W}{\partial r} \right. \\ &- \left. \left\{ -\Delta_{H} + \frac{4}{3} \left(\frac{d^{2} \ln \tilde{\rho}}{dr^{2}} + \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{1}{r} \left[3 \frac{d \ln \nu}{dr} + \frac{d \ln \tilde{\rho}}{dr} \right] \right) \right\} W \right], \end{split}$$

Note: In case of a constant kinematic viscosity, the $d \ln \nu / dr$ terms vanish. If in addition, the background density is constant, the $d \ln \tilde{\rho} / dr$ terms also vanish. In that Boussinesq limit, this viscosity term would then be simplified as

$$e_r \cdot \Delta u = -\Delta_H \left[\frac{\partial^2 W}{\partial r^2} + \Delta_H W \right].$$

Using Eq. (4.10) then allows to finally write the time-evolution equation for the poloidal potential $W_{\ell mn}$:

$$E \frac{\ell(\ell+1)}{r^{2}} \left[\left\{ \frac{\partial}{\partial t} + \nu \frac{\ell(\ell+1)}{r^{2}} + \frac{4}{3} \nu \left(\frac{d^{2} \ln \tilde{\rho}}{dr^{2}} + \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{1}{r} \left[3 \frac{d \ln \nu}{dr} + \frac{d \ln \tilde{\rho}}{dr} \right] \right) \right\} C_{n}$$

$$-\nu \left\{ 2 \frac{d \ln \nu}{dr} - \frac{1}{3} \frac{d \ln \tilde{\rho}}{dr} \right\} C'_{n}$$

$$-\nu C''_{n} \qquad \left[W_{\ell m n} \right]$$

$$+ \left[C'_{n} - \frac{d \ln \tilde{\rho}}{dr} C_{n} \right] \qquad P_{\ell m n}$$

$$- \left[\frac{Ra E}{Pr} \tilde{\rho} g(r) \right] C_{n} \qquad s_{\ell m n}$$

$$- \left[\frac{Ra \xi E}{Sc} \tilde{\rho} g(r) \right] C_{n} \qquad \xi_{\ell m n}$$

$$= \mathcal{N}_{\ell m}^{W} = \int d\Omega Y_{\ell}^{m \star} \mathcal{N}^{W} = \int d\Omega Y_{\ell}^{m \star} e_{r} \cdot \mathbf{F}.$$

$$(4.20)$$

Here, $d\Omega$ is the spherical surface element. We use the summation convention for the Chebyshev index n. The radial derivatives of Chebyshev polynomials are denoted by primes.

See also:

The exact computation of the linear terms of (4.20) are coded in the subroutines get wpMat

4.4.2 Equation for the toroidal potential Z

The temporal evolution of Z is obtained by taking the radial component of the curl of the Navier-Stokes equation (i.e. $e_r \cdot \nabla \times$). For the time derivative, one gets using (4.2):

$$e_{r} \cdot \nabla \times \left(\frac{\partial \tilde{\rho} u}{\partial t} \right) = \frac{\partial}{\partial t} (e_{r} \cdot \nabla \times \tilde{\rho} u) = -\frac{\partial}{\partial t} (\Delta_{H} Z) = -\Delta_{H} \frac{\partial Z}{\partial t}.$$

The pressure gradient, one has

$$\nabla \times \left[\tilde{\rho} \nabla \left(\frac{p'}{\tilde{\rho}} \right) \right] = \nabla \tilde{\rho} \times \nabla \left(\frac{p'}{\tilde{\rho}} \right) + \underbrace{\tilde{\rho} \nabla \times \left[\nabla \left(\frac{p'}{\tilde{\rho}} \right) \right]}_{0}.$$

This expression has no component along e_r , as a consequence, there is no pressure gradient contribution here. The gravity term also vanishes as $\nabla \times (\tilde{\rho}g(r)e_r)$ has no radial component.

$$\begin{split} \boldsymbol{e_r} \cdot \boldsymbol{\nabla} \times \left[\boldsymbol{\nabla} \cdot \boldsymbol{\mathsf{S}} \right] &= -\nu \, \Delta_H \left[\frac{\partial^2 Z}{\partial r^2} + \left(\frac{d \ln \nu}{dr} - \frac{d \ln \tilde{\rho}}{dr} \right) \, \frac{\partial Z}{\partial r} \right. \\ &\left. - \left(\frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \frac{d \ln \nu}{dr} + \frac{d^2 \ln \tilde{\rho}}{dr^2} + \frac{2}{r} \frac{d \ln \tilde{\rho}}{dr} - \Delta_H \right) Z \right]. \end{split}$$

Note: Once again, this viscous term can be greatly simplified in the Boussinesq limit:

$$\boldsymbol{e_r} \cdot \boldsymbol{\nabla} \times (\Delta \boldsymbol{u}) = -\Delta_H \left[\frac{\partial^2 Z}{\partial r^2} + \Delta_H Z \right].$$

Using Eq. (4.10) then allows to finally write the time-evolution equation for the poloidal potential $Z_{\ell mn}$:

$$E \frac{\ell(\ell+1)}{r^{2}} \left[\left\{ \frac{\partial}{\partial t} + \nu \frac{\ell(\ell+1)}{r^{2}} + \nu \left(\frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \frac{d \ln \nu}{dr} + \frac{d^{2} \ln \tilde{\rho}}{dr^{2}} + \frac{2}{r} \frac{d \ln \tilde{\rho}}{dr} \right) \right\} C_{n}$$

$$-\nu \left(\frac{d \ln \nu}{dr} - \frac{d \ln \tilde{\rho}}{dr} \right) C'_{n}$$

$$-\nu C''_{n} \qquad \right] \quad Z_{\ell m n}$$

$$= \mathcal{N}_{\ell m}^{Z} = \int d\Omega Y_{\ell}^{m \star} \mathcal{N}^{Z} = \int d\Omega Y_{\ell}^{m \star} \mathbf{e}_{r} \cdot (\nabla \times \mathbf{F}) .$$

$$(4.21)$$

See also:

The exact computation of the linear terms of (4.21) are coded in the subroutines get_zMat

4.4.3 Equation for pressure *P*

The evolution of equation for pressure is obtained by taking the horizontal divergence (i.e. $\nabla_H \cdot$) of the Navier-Stokes equation. This operator is defined such that

$$\nabla_H \cdot \boldsymbol{a} = r \sin \frac{\partial (\sin \theta \, a_\theta)}{\partial \theta} + r \sin \frac{\partial a_\phi}{\partial \phi}$$

This relates to the total divergence via:

$$oldsymbol{
abla} \cdot oldsymbol{a} = rac{1}{r^2} rac{\partial (r^2 a_r)}{\partial r} + oldsymbol{
abla}_H \cdot oldsymbol{a}.$$

The time-derivative term is thus expressed by

$$\begin{split} \boldsymbol{\nabla}_{H} \cdot \left(\tilde{\rho} \frac{\partial \boldsymbol{u}}{\partial t} \right) &= \frac{\partial}{\partial t} \left[\boldsymbol{\nabla}_{H} \cdot \left(\tilde{\rho} \boldsymbol{u} \right) \right], \\ &= \frac{\partial}{\partial t} \left[\boldsymbol{\nabla} \cdot \left(\tilde{\rho} \boldsymbol{u} \right) - \frac{1}{r^{2}} \frac{\partial (r^{2} \tilde{\rho} u_{r})}{\partial r} \right], \\ &= -\frac{\partial}{\partial t} \left[\frac{\partial (\tilde{\rho} u_{r})}{\partial r} + \frac{2 \tilde{\rho} u_{r}}{r} \right], \\ &= \frac{\partial}{\partial t} \left[\frac{\partial (\Delta_{H} W)}{\partial r} + \frac{2}{r} \Delta_{H} W \right], \\ &= \Delta_{H} \frac{\partial}{\partial t} \left(\frac{\partial W}{\partial r} \right). \end{split}$$

We note that the gravity term vanishes since $\nabla_H \cdot (\tilde{\rho}g(r)e_r) = 0$. Concerning the pressure gradient, one has

$$-\boldsymbol{\nabla}_{H}\cdot\left[\tilde{\rho}\boldsymbol{\nabla}\left(\frac{p'}{\tilde{\rho}}\right)\right]=-\left\{\boldsymbol{\nabla}\cdot\left[\tilde{\rho}\boldsymbol{\nabla}\left(\frac{p'}{\tilde{\rho}}\right)\right]-\frac{1}{r^{2}}\frac{\partial}{\partial r}\left[r^{2}\tilde{\rho}\frac{\partial}{\partial r}\left(\frac{p'}{\tilde{\rho}}\right)\right]\right\}=-\Delta_{H}\,p'.$$

The viscosity term then reads

$$\begin{split} \boldsymbol{\nabla}_{H} \cdot \left(\boldsymbol{\nabla} \cdot \boldsymbol{\mathsf{S}} \right) = & \nu \, \Delta_{H} \left[\frac{\partial^{3} W}{\partial r^{3}} + \left(\frac{d \ln \nu}{dr} - \frac{d \ln \tilde{\rho}}{dr} \right) \frac{\partial^{2} W}{\partial r^{2}} \right. \\ & - \left[\frac{d^{2} \ln \tilde{\rho}}{dr^{2}} + \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \left(\frac{d \ln \nu}{dr} + \frac{d \ln \tilde{\rho}}{dr} \right) - \Delta_{H} \right] \frac{\partial W}{\partial r} \\ & - \left(\frac{2}{3} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} + \frac{d \ln \nu}{dr} \right) \Delta_{H} W \right]. \end{split}$$

Note: Once again, this viscous term can be greatly simplified in the Boussinesq limit:

$$\nabla_H \cdot (\Delta \boldsymbol{u}) = -\Delta_H \left[\frac{\partial^3 W}{\partial r^3} + \Delta_H \frac{\partial W}{\partial r} - \frac{2}{r} \Delta_H W \right].$$

Using Eq. (4.10) then allows to finally write the equation for the pressure $P_{\ell mn}$:

$$E\frac{\ell(\ell+1)}{r^2} \left[-\nu \left(\frac{2}{3} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} + \frac{d \ln \nu}{dr} \right) \frac{\ell(\ell+1)}{r^2} C_n \right]$$

$$\left\{ \frac{\partial}{\partial t} + \nu \frac{\ell(\ell+1)}{r^2} + \nu \left[\frac{d^2 \ln \tilde{\rho}}{dr^2} + \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \left(\frac{d \ln \nu}{dr} + \frac{d \ln \tilde{\rho}}{dr} \right) \right] \right\} C'_n$$

$$-\nu \left(\frac{d \ln \nu}{dr} - \frac{d \ln \tilde{\rho}}{dr} \right) C''_n$$

$$-\nu C'''_n \qquad \right] W_{\ell m n}$$

$$+ \left[\frac{\ell(\ell+1)}{r^2} \right] C_n \qquad P_{\ell m n}$$

$$= \mathcal{N}_{\ell m}^P = -\int d\Omega Y_{\ell}^{m*} \mathcal{N}^P = -\int d\Omega Y_{\ell}^{m*} \nabla_H \cdot \mathbf{F} .$$

$$(4.22)$$

See also:

The exact computation of the linear terms of (4.22) are coded in the subroutines get_wpMat

Note: We note that the terms on the left hand side of (4.20), (4.21) and (4.22) resulting from the viscous term, the pressure gradient, the buoyancy term, and the explicit time derivative completely decouple in spherical harmonic degree and order.

The terms that do not decouple, namely Coriolis force, Lorentz force and advection of momentum, are collected on the right-hand side of (4.20), (4.21) and (4.22) into the forcing term F:

$$\mathbf{F} = -2\,\tilde{\rho}\,\mathbf{e}_{z} \times \mathbf{u} - E\,\tilde{\rho}\,\mathbf{u} \cdot \nabla\,\mathbf{u} + \frac{1}{Pm}\left(\nabla \times \mathbf{B}\right) \times \mathbf{B}.$$
(4.23)

Resolving F into potential functions is not required. Its numerical evaluation is discussed below.

4.4.4 Equation for entropy s

The equation for the entropy (or temperature in the Boussinesq limit) is given by

$$\frac{1}{Pr} \left[\left(Pr \frac{\partial}{\partial t} + \kappa \frac{\ell(\ell+1)}{r^2} \right) C_n \right] \\
-\kappa \left(\frac{d \ln \kappa}{dr} + \frac{d \ln \tilde{\rho}}{dr} + + \frac{d \ln \tilde{T}}{dr} + \frac{2}{r} \right) C'_n \right] \\
-\kappa C''_n \qquad \left[s_{\ell m n} \right] s_{\ell m n}$$

$$= \mathcal{N}_{\ell m}^S = \int d\Omega Y_{\ell}^{m \star} \mathcal{N}^S = \int d\Omega Y_{\ell}^{m \star} \left[-\mathbf{u} \cdot \nabla s + \frac{Pr Di}{Ra} \frac{1}{\tilde{\rho} \tilde{T}} \left(\Phi_{\nu} + \frac{\lambda}{Pm^2 E} j^2 \right) \right]. \tag{4.24}$$

In this expression, $j = \nabla \times B$ is the current. Once again, the numerical evaluation of the right-hand-side (i.e. the non-linear terms) is discussed *below*.

See also:

The exact computation of the linear terms of (4.24) are coded in the subroutines get_sMat

4.4.5 Equation for chemical composition ξ

The equation for the chemical composition is given by

$$\frac{1}{Sc} \left[\left(Sc \frac{\partial}{\partial t} + \kappa_{\xi} \frac{\ell(\ell+1)}{r^{2}} \right) C_{n} \right.$$

$$-\kappa_{\xi} \left(\frac{d \ln \kappa_{\xi}}{dr} + \frac{d \ln \tilde{\rho}}{dr} + + \frac{2}{r} \right) C'_{n}$$

$$-\kappa_{\xi} C''_{n} \qquad \left] \quad \xi_{\ell m n} \right.$$

$$= \mathcal{N}_{\ell m}^{\xi} = \int d\Omega Y_{\ell}^{m \star} \mathcal{N}^{\xi} = \int d\Omega Y_{\ell}^{m \star} \left[-\mathbf{u} \cdot \mathbf{\nabla} \xi \right] .$$
(4.25)

Once again, the numerical evaluation of the right-hand-side (i.e. the non-linear term) is discussed below.

See also:

The exact computation of the linear terms of (4.25) are coded in the subroutines get_xiMat

4.4.6 Equation for the poloidal magnetic potential g

The equation for the poloidal magnetic potential is the radial component of the dynamo equation since

$$e_{r} \cdot \left(\frac{\partial \boldsymbol{B}}{\partial t} \right) = \frac{\partial}{\partial t} (e_{r} \cdot \boldsymbol{B}) = -\Delta_{H} \frac{\partial g}{\partial t}.$$

The spectral form then reads

$$\frac{\ell(\ell+1)}{r^2} \left[\left(\frac{\partial}{\partial t} + \frac{1}{Pm} \lambda \frac{\ell(\ell+1)}{r^2} \right) C_n - \frac{1}{Pm} \lambda C_n'' \right] g_{\ell m n}$$

$$= \mathcal{N}_{\ell m}^g = \int d\Omega Y_{\ell}^{m \star} \mathcal{N}^g = \int d\Omega Y_{\ell}^{m \star} e_{\mathbf{r}} \cdot \mathbf{D}.$$
(4.26)

See also:

The exact computation of the linear terms of (4.26) are coded in the subroutines get_bMat

4.4.7 Equation for the toroidal magnetic potential h

The equation for the toroidal magnetic field coefficient reads

$$\frac{\ell(\ell+1)}{r^2} \left[\left(\frac{\partial}{\partial t} + \frac{1}{Pm} \lambda \frac{\ell(\ell+1)}{r^2} \right) C_n - \frac{1}{Pm} \frac{d\lambda}{dr} C'_n - \frac{1}{Pm} \lambda C''_n - \frac{1}{Pm} \lambda C''_n \right] h_{\ell m n}$$

$$= \mathcal{N}_{\ell m}^h = \int d\Omega Y_{\ell}^{m*} \mathcal{N}^h = \int d\Omega Y_{\ell}^{m*} \mathbf{e}_{\mathbf{r}} \cdot (\mathbf{\nabla} \times \mathbf{D}) . \tag{4.27}$$

See also:

The exact computation of the linear terms of (4.27) are coded in the subroutines get_bMat

Note: We note that the terms on the left hand side of (4.26) and (4.27) resulting from the magnetic diffusion term and the explicit time derivative completely decouple in spherical harmonic degree and order.

The dynamo term does not decouple:

$$D = \nabla \times (\boldsymbol{u} \times \boldsymbol{B}) . \tag{4.28}$$

We have now derived a full set of equations (4.20), (4.21), (4.22), (4.24), (4.26) and (4.27), each describing the evolution of a single spherical harmonic mode of the six unknown fields (assuming that the terms on the right hand side are given). Each equation couples N+1 Chebyshev coefficients for a given spherical harmonic mode (ℓ, m) . Typically, a collocation method is employed to solve for the Chebyshev coefficients. This means that the equations are required to be exactly satisfied at N-1 grid points defined by the equations (4.18) and (4.19). Excluded are the points $r=r_i$ and $r=r_o$, where the *boundary conditions* provide additional constraints on the set of Chebyshev coefficients.

4.5 Time-stepping schemes

Implicit time stepping schemes theoretically offer increased stability and allow for larger time steps. However, fully implicit approaches have the disadvantage that the nonlinear-terms couple all spherical harmonic modes. The potential

gain in computational speed is therefore lost at higher resolution, where one very large matrix has to be dealt with rather than a set of much smaller ones. Similar considerations hold for the Coriolis force, one of the dominating forces in the system and therefore a prime candidate for implicit treatment. However, the Coriolis term couples modes (ℓ, m, n) with $(\ell+1, m, n)$ and $(\ell-1, m, n)$ and also couples poloidal and toroidal flow potentials. An implicit treatment of the Coriolis term therefore also results in a much larger (albeit sparse) inversion matrix.

We consequently adopt in MagIC a mixed implicit/explicit algorithm. The general differential equation in time can be written in the form

$$\frac{\partial}{\partial t}x + \mathcal{I}(x,t) = \mathcal{E}(x,t) .$$

where \mathcal{I} denotes the terms treated in an implicit time step and \mathcal{E} the terms treated explicitly, i.e.~the nonlinear and Coriolis contributions. The discretized implicit time step is given by

$$\left(\frac{x(t+\delta t)-x(t)}{\delta t}\right)_{I} = -\alpha \,\mathcal{I}(x,t+\delta t) - (1-\alpha)\,\mathcal{I}(x,t) \ .$$

where α is the weight of the new time step. For $\alpha = 0.5$ we recover a classic Crank-Nicolson algorithm.

A second order Adams-Bashforth scheme is used for the explicit time step:

$$\left(\frac{x(t+\delta t)-x(t)}{\delta t}\right)_E = \frac{3}{2} \mathcal{E}(x,t) - \frac{1}{2} \mathcal{E}(x,t-\delta t) .$$

The combination of both steps yields

$$\frac{x(t+\delta t)}{\delta t} + \alpha \, \mathcal{I}(x,t+\delta t) = \frac{x(t)}{\delta t} - (1-\alpha) \, \mathcal{I}(x,t) + \frac{3}{2} \, \mathcal{E}(x,t) - \frac{1}{2} \, \mathcal{E}(x,t-\delta t) .$$

In the code such an equation is formulated for each unknown spectral coefficient (expect pressure) of spherical harmonic degree ℓ and order m and for each radial grid point r_k . Because non-linear terms and the Coriolis force are treated explicitly, the equations decouple for all spherical modes. The different radial grid points, however, couple via the Chebychev modes and form a linear algebraic system of equations that can be solved with standard methods for the different spectral contributions.

For example the respective system of equations for the modes of the poloidal magnetic potential g results from considering the radial component of the dynamo equation:

$$(\mathcal{A}_{kn} + \alpha \,\mathcal{I}_{kn}) \,g_{\ell mn}(t + \delta t) = (\mathcal{A}_{kn} - (1 - \alpha)\,\mathcal{I}_{kn}) \,g_{\ell mn}(t) + \frac{3}{2}\,\mathcal{E}_{k\ell m}(t) - \frac{1}{2}\,\mathcal{E}_{k\ell m}(t - \delta t) \tag{4.29}$$

with

$$\mathcal{A}_{kn} = \frac{\ell(\ell+1)}{r_k^2} \frac{1}{\delta t} \mathcal{C}_{nk} ,$$

$$\mathcal{I}_{kn} = \frac{\ell(\ell+1)}{r_k^2} \frac{1}{Pm} \left(\frac{\ell(\ell+1)}{r_k^2} \, \mathcal{C}_{nk} - \mathcal{C}_{nk}'' \right) ,$$

and $C_{nk} = C_n(r_k)$. A_{kn} is a matrix that converts the poloidal field modes $g_{\ell mn}$ to the radial magnetic field $B_r(r_k, \ell m)$ for a given spherical harmonic contribution with an additional division by the time step δt :

Here k and n number the radial grid points and the Chebychev coefficients, respectively. Note that the Einstein sum convention is used for Chebychev modes n.

 \mathcal{I}_{kn} is the matrix describing the implicit contribution which is purely diffusive here. Neither \mathcal{A}_{kn} nor \mathcal{I}_{kn} depend on time but the former needs to be updated when the time step δt is changed. The only explicit contribution is the nonlinear dynamo term

$$\mathcal{E}_{k\ell m}(t) = \mathcal{N}_{k\ell m}^g = \int d\Omega Y_{\ell}^{m\star} \mathbf{e}_{r} \cdot \mathbf{D}(t, r_k, \theta, \phi) .$$

 $\mathcal{E}_{k\ell m}$ is a one dimensional vector for all spherical harmonic combinations ℓm .

How are these operations organized in the code? Within MagIC the poloidal magnetic field potential is called b. The implicit step for the current time t and the explicit step for the previous time $t - \delta t$ is combined into one two-dimensional array

$$\label{eq:loss_loss} \texttt{dbdtLast}(k,lm) = -\frac{1}{2} \; \mathcal{E}_{k\ell m}(t-\delta t) - (1-\alpha) \; \mathcal{I}_{kn} \; g_{\ell mn}(t) \; .$$

where k numbers the first dimension and the second dimension lm numbers the spherical harmonic modes. The explicit time step part is called dbdt in MagIC:

$$dbdt(k, \ell m) = \mathcal{E}_{k\ell m}.$$

The combination of left hand side of (4.29) provides the time stepping matrix for g:

$$bmat(k, n, \ell) = A_{kn} + \alpha \mathcal{I}_{kn} .$$

There is a different time stepping matrix for each spherical harmonic degree ℓ . The linear system of equations solved for the mode $b(k, \ell m)$ at time $t = t + \delta t$ is then

$$\begin{aligned} \operatorname{bmat}(k,n,\ell) \star \operatorname{b}_{i+1}(n,\ell m) = & \operatorname{wl} \star \operatorname{dbdt}(k,\ell m) + \operatorname{w2} \star \operatorname{dbdtLast}(k,\ell m) + \\ & \operatorname{Odt} \star \operatorname{dLh}(\ell) \star \operatorname{Or2}(k) \star \operatorname{b}_{i}(n,\ell m) \\ = & \operatorname{rhs}(k,\ell m) \end{aligned}$$

with

$${\rm w2} = -1/2 \frac{\delta t}{\delta t_{old}} \ , \ {\rm w1} = 1 - {\rm w2} \ , \ {\rm Odt} = 1/\delta t \ , \ {\rm dLh}(\ell) = \ell(\ell+1) \ , \ {\rm Or2}(k) = 1/r_k^2.$$

The respective equations for the poloidal flow potential are somewhat more complex and involve coupling to the pressure.....

Note: The poloidal flow potential (4.20) and the pressure (4.22) are nevertheless coupled for a given spherical harmonic mode. Likewise the poloidal flow and entropy (or temperature) equations should also couple, but here MagIC takes the shortcut of updating entropy first and using the already updated value for an explicit treatment of buoyancy.

Courant's condition offers a guideline concerning the value of δt , demanding that δt should be smaller than the advection time between two grid points. Strong Lorentz forces require an additional stability criterion that is obtained by replacing the flow speed by Alfvén's velocity in a modified Courant criterion. The explicit treatment of the Coriolis force requires that the time step is limited to a fraction of the rotation period, which may be the relevant criterion at low Ekman number when flow and magnetic field remain weak. Non-homogeneous grids and other numerical effects generally require an additional safety factor in the choice of δt .

4.6 Coriolis force and nonlinear terms

4.6.1 Nonlinear terms entering the equation for W

The nonlinear term \mathcal{N}^W that enters the equation for the poloidal potential (4.20) contains the radial component of the advection, the Lorentz force and Coriolis force. In spherical coordinate, the two first contributions read:

$$\tilde{\rho}\left(\boldsymbol{u}\cdot\boldsymbol{\nabla}\boldsymbol{u}\right) = \begin{cases}
A_{r} \\
A_{\theta} \\
A_{\phi}
\end{cases} = \begin{cases}
-\tilde{\rho}E\left(u_{r}\frac{\partial u_{r}}{\partial r} + \frac{u_{\theta}}{r}\frac{\partial u_{r}}{\partial \theta} + \frac{u_{\phi}}{r\sin\theta}\frac{\partial u_{r}}{\partial \phi} - \frac{u_{\theta}^{2} + u_{\phi}^{2}}{r}\right) + \frac{1}{Pm}\left(j_{\theta}B_{\phi} - j_{\phi}B_{\theta}\right), \\
-\tilde{\rho}E\left(u_{r}\frac{\partial u_{\theta}}{\partial r} + \frac{u_{\theta}}{r}\frac{\partial u_{\theta}}{\partial \theta} + \frac{u_{\phi}}{r\sin\theta}\frac{\partial u_{\theta}}{\partial \phi} + \frac{u_{r}u_{\theta}}{r} - \frac{\cos\theta}{r\sin\theta}u_{\phi}^{2}\right) + \frac{1}{Pm}\left(j_{\phi}B_{r} - j_{r}B_{\phi}\right), \\
-\tilde{\rho}E\left(u_{r}\frac{\partial u_{\phi}}{\partial r} + \frac{u_{\theta}}{r}\frac{\partial u_{\phi}}{\partial \theta} + \frac{u_{\phi}}{r\sin\theta}\frac{\partial u_{\phi}}{\partial \phi} + \frac{u_{r}u_{\phi}}{r} + \frac{\cos\theta}{r\sin\theta}u_{\theta}u_{\phi}\right) + \frac{1}{Pm}\left(j_{r}B_{\theta} - j_{\theta}B_{r}\right), \end{cases}$$
(4.30)

The Coriolis force can be expressed as a function of the potentials W and Z using (4.4)

$$2\tilde{\rho}\boldsymbol{e_r}\cdot(\boldsymbol{u}\times\boldsymbol{e_z})=2\sin\theta\,\tilde{\rho}u_{\phi}=\frac{2}{r}\left(\frac{\partial^2W}{\partial r\partial\phi}-\sin\theta\frac{\partial Z}{\partial\theta}\right).$$

The nonlinear terms that enter the equation for the poloidal potential (4.20) thus reads:

$$\mathcal{N}^W = \frac{2}{r} \left(\frac{\partial^2 W}{\partial r \partial \phi} - \sin \theta \frac{\partial Z}{\partial \theta} \right) + \mathcal{A}_r.$$

The θ -derivative entering the radial component of the Coriolis force is thus the operator ϑ_2 defined in (4.12). Using the recurrence relation, one thus finally gets in spherical harmonic space:

$$\mathcal{N}_{\ell m}^{W} = \frac{2}{r} \left[im \frac{\partial W_{\ell}^{m}}{\partial r} - (\ell - 1) c_{\ell}^{m} Z_{\ell-1}^{m} + (\ell + 2) c_{\ell+1}^{m} Z_{\ell+1}^{m} \right] + \mathcal{A}_{r\ell}^{m}.$$
(4.31)

To get this expression, we need to first compute \mathcal{A}_r in the physical space. This term is computed in the subroutine get_nl in the module grid_space_arrays_mod. \mathcal{A}_r is then transformed to the spectral space by using a Legendre and a Fourier transform to produce $\mathcal{A}_{r\ell}^m$.

See also:

The final calculations of (4.31) are done in the subroutine get_td .

4.6.2 Nonlinear terms entering the equation for Z

The nonlinear term \mathcal{N}^Z that enters the equation for the toroidal potential (4.21) contains the radial component of the curl of the advection and Coriolis force. The Coriolis force can be rewritten as a function of W and Z:

$$\begin{split} \boldsymbol{e_r} \cdot \boldsymbol{\nabla} \times \left[(2\tilde{\rho}\boldsymbol{u}) \times \boldsymbol{e_z} \right] &= 2\boldsymbol{e_r} \cdot \left[(\boldsymbol{e_z} \cdot \boldsymbol{\nabla})(\tilde{\rho}\boldsymbol{u}) \right], \\ &= 2 \left[\cos\theta \frac{\partial (\tilde{\rho}u_r)}{\partial r} - \frac{\sin\theta}{r} \frac{\partial (\tilde{\rho}u_r)}{\partial \theta} + \frac{\tilde{\rho}u_\theta \sin\theta}{r} \right], \\ &= 2 \left[-\cos\theta \frac{\partial}{\partial r} (\Delta_H W) + \frac{\sin\theta}{r} \frac{\partial}{\partial \theta} (\Delta_H W) + \frac{\sin\theta}{r^2} \frac{\partial^2 W}{\partial r \partial \theta} + \frac{1}{r^2} \frac{\partial Z}{\partial \phi} \right]. \end{split}$$

Using the ϑ operators defined in (4.12)-(4.15) then allows to rewrite the Coriolis force in the following way:

$$[\boldsymbol{e_r} \cdot \boldsymbol{\nabla} \times [(2\tilde{\rho}\boldsymbol{u}) \times \boldsymbol{e_z}] = \frac{2}{r^2} \left(\vartheta_3 \frac{\partial W}{\partial r} - \frac{1}{r} \vartheta_4 W + \frac{\partial Z}{\partial \phi} \right).$$
 (4.32)

The contributions of nonlinear advection and Lorentz forces that enter the equation for the toroidal potential are written this way:

$$\frac{1}{r\sin\theta} \left[\frac{\partial(\sin\theta \mathcal{A}_{\phi})}{\partial\theta} - \frac{\partial\mathcal{A}_{\theta}}{\partial\phi} \right] .$$

To make use of the recurrence relations (4.12)-(4.15), the actual strategy is to follow the following steps:

- 1. Compute the quantities $A_{\phi}/r\sin\theta$ and $A_{\theta}/r\sin\theta$ in the physical space. In the code, this step is computed in the subroutine get_nl in the module grid_space_arrays_mod.
- 2. Transform $A_{\phi}/r\sin\theta$ and $A_{\theta}/r\sin\theta$ to the spectral space (thanks to a Legendre and a Fourier transform). In MagIC, this step is computed in the modules $legendre_grid_to_spec$ and fft. After this step $\mathcal{A}t_{\ell}^{m}$ and $\mathcal{A}p_{\ell}^{m}$ are defined.
- 3. Calculate the colatitude and theta derivatives using the recurrence relations:

$$\vartheta_1 \mathcal{A} p_\ell^m - \frac{\partial \mathcal{A} t_\ell^m}{\partial \phi} \,. \tag{4.33}$$

Using (4.32) and (4.33), one thus finally gets

$$\mathcal{N}_{\ell m}^{Z} = \frac{2}{r^{2}} \left[(\ell - 1)(\ell + 1) c_{\ell}^{m} \frac{\partial W_{\ell-1}^{m}}{\partial r} + \ell(\ell + 2) c_{\ell+1}^{m} \frac{\partial W_{\ell+1}^{m}}{\partial r} - \frac{\ell(\ell - 1)(\ell + 1)}{r} c_{\ell}^{m} W_{\ell-1}^{m} + \frac{\ell(\ell + 1)(\ell + 2)}{r} c_{\ell+1}^{m} W_{\ell+1}^{m} + im Z_{\ell}^{m} \right] + (\ell + 1) c_{\ell}^{m} \mathcal{A} p_{\ell-1}^{m} - \ell c_{\ell+1}^{m} \mathcal{A} p_{\ell+1}^{m} - im \mathcal{A} t_{\ell}^{m}.$$
(4.34)

See also:

The final calculations of (4.34) are done in the subroutine get_td .

4.6.3 Nonlinear terms entering the equation for P

The nonlinear term \mathcal{N}^P that enters the equation for the pressure (4.22) contains the horizontal divergence of the advection and Coriolis force. The Coriolis force can be rewritten as a function of W and Z:

$$\begin{split} \boldsymbol{\nabla}_{H} \cdot \left[(2\tilde{\rho}\boldsymbol{u}) \times \boldsymbol{e}_{\boldsymbol{z}} \right] &= 2\boldsymbol{e}_{\boldsymbol{z}} \cdot \left[\boldsymbol{\nabla} \times (\tilde{\rho}\boldsymbol{u}) \right] - \left(\frac{\partial}{\partial r} + \frac{2}{r} \right) \left[\boldsymbol{e}_{\boldsymbol{r}} \cdot (2\tilde{\rho}\boldsymbol{u} \times \boldsymbol{e}_{\boldsymbol{z}}) \right], \\ &= -2\cos\theta \, \Delta_{H} Z - 2\sin\theta \left[-\frac{1}{r\sin\theta} \frac{\partial}{\partial \phi} \left(\frac{\partial^{2}}{\partial r^{2}} + \Delta_{H} \right) W + \frac{1}{r} \frac{\partial^{2}Z}{\partial r\partial\theta} \right] \\ &- \left(\frac{\partial}{\partial r} + \frac{2}{r} \right) \left[2\sin\theta \tilde{\rho} u_{\phi} \right], \\ &= 2 \left[\frac{1}{r} \left(\Delta_{H} + \frac{\partial^{2}}{\partial r^{2}} \right) \frac{\partial W}{\partial \phi} - \cos\theta \Delta_{H} Z - \frac{\sin\theta}{r} \frac{\partial^{2}Z}{\partial r\partial\theta} \right] \\ &- \left(\frac{\partial}{\partial r} + \frac{2}{r} \right) \left[\frac{2}{r} \left(\frac{\partial^{2}W}{\partial r\partial\phi} - \sin\theta \frac{\partial Z}{\partial\theta} \right) \right], \\ &= 2 \left(\frac{\Delta_{H}}{r} \frac{\partial W}{\partial \phi} - \frac{1}{r^{2}} \frac{\partial^{2}W}{\partial \phi\partial r} - \cos\theta \Delta_{H} Z + \frac{\sin\theta}{r^{2}} \frac{\partial Z}{\partial\theta} \right). \end{split}$$

Using the ϑ operators defined in (4.14)-(4.15) then allows to rewrite the Coriolis force in the following way:

$$\nabla_{H} \cdot \left[(2\tilde{\rho}\boldsymbol{u}) \times \boldsymbol{e}_{\boldsymbol{z}} \right] = \frac{2}{r^{2}} \left(-\frac{L_{H}}{r} \frac{\partial W}{\partial \phi} - \frac{\partial^{2} W}{\partial \phi \partial r} + \vartheta_{3} Z \right). \tag{4.35}$$

The contributions of nonlinear advection and Lorentz forces that enter the equation for pressure are written this way:

$$\frac{1}{r\sin\theta} \left[\frac{\partial (\sin\theta \mathcal{A}_{\theta})}{\partial \theta} + \frac{\partial \mathcal{A}_{\phi}}{\partial \phi} \right] .$$

To make use of the recurrence relations (4.12)-(4.15), we then follow the same three steps as for the advection term entering the equation for Z.

$$\vartheta_1 \mathcal{A} t_\ell^m + \frac{\partial \mathcal{A} p_\ell^m}{\partial \phi} \,. \tag{4.36}$$

Using (4.35) and (4.36), one thus finally gets

$$\mathcal{N}_{\ell m}^{P} = \frac{2}{r^{2}} \left[-im \frac{\ell(\ell+1)}{r} W_{\ell}^{m} - im \frac{\partial W_{\ell}^{m}}{\partial r} + (\ell-1)(\ell+1) c_{\ell}^{m} Z_{\ell-1}^{m} + \ell(\ell+2) c_{\ell+1}^{m} Z_{\ell+1}^{m} \right] + (\ell+1) c_{\ell}^{m} \mathcal{A} t_{\ell-1}^{m} - \ell c_{\ell+1}^{m} \mathcal{A} t_{\ell+1}^{m} + im \mathcal{A} p_{\ell}^{m}.$$
(4.37)

See also:

The final calculations of (4.37) are done in the subroutine get_td .

4.6.4 Nonlinear terms entering the equation for s

The nonlinear terms that enter the equation for entropy/temperature (4.24) are twofold: (i) the advection term, (ii) the viscous and Ohmic heating terms (that vanish in the Boussinesq limit of the Navier Stokes equations).

Viscous and Ohmic heating are directly calculated in the physical space by the subroutine get_nl in the module $grid_space_arrays_mod$. Let's introduce \mathcal{H} , the sum of the viscous and Ohmic heating terms.

$$\mathcal{H} = \frac{Pr\,Di}{Ra} \frac{1}{\tilde{\rho}\tilde{T}} \left(\Phi_{\nu} + \frac{\lambda}{Pm^2\,E} \, j^2 \right) \,.$$

Expanding this term leads to:

$$\mathcal{H} = \frac{Pr\,Di}{Ra}\,\frac{1}{\tilde{\rho}\tilde{T}}\left[\tilde{\rho}\nu\left\{2\left(\frac{\partial u_r}{\partial r}\right)^2 + 2\left(\frac{1}{r}\frac{\partial u_\theta}{\partial \theta} + \frac{u_r}{r}\right)^2 + 2\left(\frac{1}{r\sin\theta}\frac{\partial u_\phi}{\partial \phi} + \frac{u_r}{r} + \frac{\cos\theta}{r\sin\theta}u_\theta\right)^2 \right. \\ + \left.\left(r\frac{\partial}{\partial r}\left(\frac{u_\theta}{r}\right) + \frac{1}{r}\frac{\partial u_r}{\partial \theta}\right)^2 + \left(r\frac{\partial}{\partial r}\left(\frac{u_\phi}{r}\right) + \frac{1}{r\sin\theta}\frac{\partial u_r}{\partial \phi}\right)^2 \right. \\ + \left.\left(\frac{\sin\theta}{r}\frac{\partial}{\partial \theta}\left(\frac{u_\phi}{\sin\theta}\right) + \frac{1}{r\sin\theta}\frac{\partial u_\theta}{\partial \phi}\right)^2 - \frac{2}{3}\left(\frac{d\ln\tilde{\rho}}{dr}u_r\right)^2\right\} \\ + \frac{\lambda}{Pm^2E}\left\{j_r^2 + j_\theta^2 + j_\phi^2\right\}\right].$$

$$(4.38)$$

This term is then transformed to the spectral space with a Legendre and a Fourier transform to produce \mathcal{H}_{ℓ}^{m} .

The treatment of the advection term $-\mathbf{u}\cdot\nabla s$ is a bit different. It is in a first step rearranged as follows

$$-\boldsymbol{u}\cdot\boldsymbol{\nabla}s=-\frac{1}{\tilde{\rho}}\left[\boldsymbol{\nabla}\cdot(\tilde{\rho}s\boldsymbol{u})-s\underbrace{\boldsymbol{\nabla}\cdot(\tilde{\rho}\boldsymbol{u})}_{-0}\right]\;.$$

The quantities that are calculated in the physical space are thus simply the product of entropy/temperature s by the velocity components. This defines three variables defined in the grid space that are computed in the subroutine get_nl:

$$\mathcal{US}_r = \tilde{\rho} s u_r$$
, $\mathcal{US}_{\theta} = \tilde{\rho} s u_{\theta}$, $\mathcal{US}_{\phi} = \tilde{\rho} s u_{\phi}$,

To get the actual advection term, one must then apply the divergence operator to get:

$$-\boldsymbol{u}\cdot\boldsymbol{\nabla}s = -\frac{1}{\tilde{\rho}}\left[\frac{1}{r^2}\frac{\partial}{\partial r}\left(r^2\,\mathcal{U}\mathcal{S}_r\right) + \frac{1}{r\sin\theta}\frac{\partial}{\partial\theta}\left(\sin\theta\,\mathcal{U}\mathcal{S}_\theta\right) + \frac{1}{r\sin\theta}\frac{\partial\,\mathcal{U}\mathcal{S}_\phi}{\partial\phi}\right]\,.$$

To make use of the recurrence relations (4.12)-(4.15), the actual strategy is then to follow the following steps:

- 1. Compute the quantities $r^2 \mathcal{US}_r$, $\mathcal{US}_{\phi}/r \sin \theta$ and $\mathcal{US}_{\theta}/r \sin \theta$ in the physical space. In the code, this step is computed in the subroutine get_nl in the module grid_space_arrays_mod.
- 2. Transform $r^2 \mathcal{US}_r$, $\mathcal{US}_\phi/r\sin\theta$ and $\mathcal{US}_\theta/r\sin\theta$ to the spectral space (thanks to a Legendre and a Fourier transform). In MagIC, this step is computed in the modules $legendre_grid_to_spec$ and fft. After this step $\mathcal{US}r_\ell^m$, $\mathcal{US}t_\ell^m$ and $\mathcal{US}p_\ell^m$ are defined.
- 3. Calculate the colatitude and theta derivatives using the recurrence relations:

$$-\frac{1}{\tilde{\rho}} \left[\frac{1}{r^2} \frac{\partial \mathcal{US}r_{\ell}^m}{\partial r} + \vartheta_1 \mathcal{US}t_{\ell}^m + \frac{\partial \mathcal{US}p_{\ell}^m}{\partial \phi} \right]. \tag{4.39}$$

Using (4.38) and (4.39), one thus finally gets

$$\left| \mathcal{N}_{\ell m}^{S} = -\frac{1}{\tilde{\rho}} \left[\frac{1}{r^{2}} \frac{\partial \mathcal{U} \mathcal{S} r_{\ell}^{m}}{\partial r} + (\ell + 1) c_{\ell}^{m} \mathcal{U} \mathcal{S} t_{\ell-1}^{m} - \ell c_{\ell+1}^{m} \mathcal{U} \mathcal{S} t_{\ell+1}^{m} + im \mathcal{U} \mathcal{S} p_{\ell}^{m} \right] + \mathcal{H}_{\ell}^{m}. \right|$$
(4.40)

See also:

The θ and ϕ derivatives that enter (4.40) are done in the subroutine get_td . The radial derivative is computed afterwards at the very beginning of updateS.

4.6.5 Nonlinear terms entering the equation for ξ

The nonlinear term that enters the equation for chemical composition (4.25) is the advection term. This term is treated the same way as the advection term that enters the entropy equation. It is in a first step rearranged as follows

$$-\boldsymbol{u}\cdot\boldsymbol{
abla}\xi = -rac{1}{ ilde{
ho}}\left[\boldsymbol{
abla}\cdot(ilde{
ho}\xi\boldsymbol{u}) - \xi\underbrace{\boldsymbol{
abla}\cdot(ilde{
ho}\boldsymbol{u})}_{-0}
ight]\;.$$

The quantities that are calculated in the physical space are thus simply the product of composition ξ by the velocity components. This defines three variables defined in the grid space that are computed in the subroutine get_nl:

$$\mathcal{U}\mathcal{X}_r = \tilde{\rho}\xi u_r, \quad \mathcal{U}\mathcal{S}_\theta = \tilde{\rho}\xi u_\theta, \quad \mathcal{U}\mathcal{X}_\phi = \tilde{\rho}\xi u_\phi,$$

To get the actual advection term, one must then apply the divergence operator to get:

$$-\boldsymbol{u}\cdot\boldsymbol{\nabla}\xi = -\frac{1}{\tilde{\rho}}\left[\frac{1}{r^2}\frac{\partial}{\partial r}\left(r^2\mathcal{U}\mathcal{X}_r\right) + \frac{1}{r\sin\theta}\frac{\partial}{\partial\theta}\left(\sin\theta\mathcal{U}\mathcal{X}_\theta\right) + \frac{1}{r\sin\theta}\frac{\partial\mathcal{U}\mathcal{X}_\phi}{\partial\phi}\right].$$

To make use of the recurrence relations (4.12)-(4.15), the actual strategy is then to follow the following steps:

- 1. Compute the quantities $r^2 \mathcal{U} \mathcal{X}_r$, $\mathcal{U} \mathcal{X}_\phi / r \sin \theta$ and $\mathcal{U} \mathcal{X}_\theta / r \sin \theta$ in the physical space. In the code, this step is computed in the subroutine get_nl in the module grid_space_arrays_mod.
- 2. Transform $r^2 \mathcal{U} \mathcal{X}_r$, $\mathcal{U} \mathcal{X}_\phi / r \sin \theta$ and $\mathcal{U} \mathcal{X}_\theta / r \sin \theta$ to the spectral space (thanks to a Legendre and a Fourier transform). In MagIC, this step is computed in the modules $legendre_grid_to_spec$ and fft. After this step $\mathcal{U} \mathcal{X} r_\ell^m$, $\mathcal{U} \mathcal{X} t_\ell^m$ and $\mathcal{U} \mathcal{X} p_\ell^m$ are defined.

3. Calculate the colatitude and theta derivatives using the recurrence relations:

$$-\frac{1}{\tilde{\rho}} \left[\frac{1}{r^2} \frac{\partial \mathcal{U} \mathcal{X} r_\ell^m}{\partial r} + \vartheta_1 \mathcal{U} \mathcal{X} t_\ell^m + \frac{\partial \mathcal{U} \mathcal{X} p_\ell^m}{\partial \phi} \right] \,.$$

One thus finally gets

$$\mathcal{N}_{\ell m}^{\xi} = -\frac{1}{\tilde{\rho}} \left[\frac{1}{r^2} \frac{\partial \mathcal{U} \mathcal{X} r_{\ell}^m}{\partial r} + (\ell+1) c_{\ell}^m \mathcal{U} \mathcal{X} t_{\ell-1}^m - \ell c_{\ell+1}^m \mathcal{U} \mathcal{X} t_{\ell+1}^m + im \mathcal{U} \mathcal{X} p_{\ell}^m \right].$$
(4.41)

See also:

The θ and ϕ derivatives that enter (4.41) are done in the subroutine get_td . The radial derivative is computed afterwards at the very beginning of updateXi.

4.6.6 Nonlinear terms entering the equation for g

The nonlinear term that enters the equation for the poloidal potential of the magnetic field (4.26) is the radial component of the induction term (4.28). In the following we introduce the electromotive force $\mathcal{F} = u \times B$ with its three components

$$\mathcal{F}_r = u_\theta B_\phi - u_\phi B_\theta$$
, $\mathcal{F}_\theta = u_\phi B_r - u_r B_\phi$, $\mathcal{F}_\phi = u_r B_\theta - u_\theta B_r$.

The radial component of the induction term then reads:

$$\mathcal{N}^g = m{e_r} \cdot [m{
abla} imes (m{u} imes m{B})] = rac{1}{r \sin heta} \left[rac{\partial \left(\sin heta \mathcal{F}_\phi
ight)}{\partial heta} - rac{\partial \mathcal{F}_ heta}{\partial \phi}
ight] \ .$$

To make use of the recurrence relations (4.12)-(4.15), we then follow the usual following steps:

- 1. Compute the quantities $r^2 \mathcal{F}_r$, $\mathcal{F}_{\phi}/r \sin \theta$ and $\mathcal{F}_{\theta}/r \sin \theta$ in the physical space. In the code, this step is computed in the subroutine get_nl in the module grid_space_arrays_mod.
- 2. Transform $r^2 \mathcal{F}_r$, $\mathcal{F}_{\phi}/r \sin \theta$ and $\mathcal{F}_{\theta}/r \sin \theta$ to the spectral space (thanks to a Legendre and a Fourier transform). In MagIC, this step is computed in the modules $legendre_grid_to_spec$ and fft. After this step $\mathcal{F}_{r\ell}^m$, $\mathcal{F}_{\theta\ell}^m$ and $\mathcal{F}_{\phi\ell}^m$ are defined.
- 3. Calculate the colatitude and theta derivatives using the recurrence relations:

$$\vartheta_1 \mathcal{F}_{\phi\ell}^{\ m} - \frac{\partial \mathcal{F}_{\theta\ell}^{\ m}}{\partial \phi}.$$

We thus finally get

$$\mathcal{N}_{\ell m}^{g} = (\ell + 1) c_{\ell}^{m} \mathcal{F}_{\phi_{\ell-1}}^{m} - \ell c_{\ell+1}^{m} \mathcal{F}_{\phi_{\ell+1}}^{m} - im \mathcal{F}_{\theta_{\ell}}^{m}.$$
(4.42)

See also:

The final calculations of (4.42) are done in the subroutine get_td .

4.6.7 Nonlinear terms entering the equation for *h*

The nonlinear term that enters the equation for the toroidal potential of the magnetic field (4.27) is the radial component of the curl of the induction term (4.28):

$$\begin{split} \mathcal{N}^h &= \boldsymbol{e_r} \cdot \left[\boldsymbol{\nabla} \times \boldsymbol{\nabla} \times (\boldsymbol{u} \times \boldsymbol{B}) \right] = \boldsymbol{e_r} \cdot \left[\boldsymbol{\nabla} \left(\boldsymbol{\nabla} \cdot \boldsymbol{\mathcal{F}} \right) - \Delta \boldsymbol{\mathcal{F}} \right], \\ &= \frac{\partial}{\partial r} \left[\frac{1}{r^2} \frac{\partial (r^2 \mathcal{F}_r)}{\partial r} + \frac{1}{r \sin \theta} \frac{\partial (\sin \theta \, \mathcal{F}_\theta)}{\partial \theta} + \frac{1}{r \sin \theta} \frac{\partial \mathcal{F}_\phi}{\partial \phi} \right] \\ &- \Delta \mathcal{F}_r + \frac{2}{r^2} \left[\mathcal{F}_r + \frac{1}{\sin \theta} \frac{\partial (\sin \theta \, \mathcal{F}_\theta)}{\partial \theta} + \frac{1}{\sin \theta} \frac{\partial \mathcal{F}_\phi}{\partial \phi} \right], \\ &= \frac{1}{r^2} \frac{\partial}{\partial r} \left[\frac{r}{\sin \theta} \left(\frac{\partial (\sin \theta \, \mathcal{F}_\theta)}{\partial \theta} + \frac{\partial \mathcal{F}_\phi}{\partial \phi} \right) \right] - \Delta_H \, \mathcal{F}_r \, . \end{split}$$

To make use of the recurrence relations (4.12)-(4.15), we then follow the same steps than for the nonlinear terms that enter the equation for poloidal potential of the magnetic field g:

$$\frac{1}{r^2} \frac{\partial}{\partial r} \left[r^2 \left(\vartheta_1 \mathcal{F} t_\ell^m + \frac{\partial \mathcal{F} p_\ell^m}{\partial \phi} \right) \right] + L_H \mathcal{F} r_\ell^m.$$

We thus finally get

$$\mathcal{N}_{\ell m}^{h} = \ell(\ell+1) \mathcal{F} r_{\ell}^{m} + \frac{1}{r^{2}} \frac{\partial}{\partial r} \left[r^{2} \left\{ (\ell+1) c_{\ell}^{m} \mathcal{F} t_{\ell-1}^{m} - \ell c_{\ell+1}^{m} \mathcal{F} t_{\ell+1}^{m} + im \mathcal{F} p_{\ell}^{m} \right\} \right].$$
(4.43)

See also:

The θ and ϕ derivatives that enter (4.43) are computed in the subroutine get_td . The remaining radial derivative is computed afterwards at the very beginning of updateB.

4.7 Boundary conditions and inner core

4.7.1 Mechanical boundary conditions

Since the system of equations is formulated on a radial grid, boundary conditions can simply be satisfied by replacing the collocation equation at grid points r_i and r_o with appropriate expressions. The condition of zero radial flow on the boundaries implies that the poloidal potential has to vanish, i.e. $W(r_o) = 0$ and $W(r_i) = 0$. In Chebychev representation this implies

$$C_n(r)W_{\ell mn} = 0 \quad \text{at} \quad r = r_i, r_o \quad . \tag{4.44}$$

Note that the summation convention with respect to radial modes n is used again. The no-slip condition further requires that the horizontal flow components also have to vanish, provided the two boundaries are at rest. This condition is fulfilled for

$$\frac{\partial W}{\partial r} = 0$$
 and $Z = 0$,

at the respective boundary. In spectral space these conditions read

$$C'_{n}(r)W_{\ell mn} = 0 \text{ at } r = r_{i}, r_{o},$$
 (4.45)

and

$$C_n(r)Z_{\ell mn} = 0 \quad \text{at} \quad r = r_i, r_o \,, \tag{4.46}$$

for all spherical harmonic modes (ℓ, m) . The conditions (4.44)-(4.46) replace the poloidal flow potential equations (4.20) and the pressure equation (4.22), respectively, at the collocation points r_i and r_o .

If the inner-core and/or the mantle are allowed to react to torques, a condition based on the conservation of angular momentum replaces condition (4.46) for the mode ($\ell = 1, m = 0$):

$$I rac{\partial \omega}{\partial t} = \Gamma$$
 .

The tensor I denotes the moment of inertia of inner core or mantle, respectively, ω is the mantle or inner-core rotation rate relative to that of the reference frame, and Γ is the respective torque.

Free-slip boundary conditions require that the viscous stress vanishes, which in turn implies that the non-diagonal components $Sr_{r\phi}$ and $S_{r\theta}$ of the rate-of-strain tensor vanish. Translated to the spectral representation this requires

$$\left[\mathcal{C}_n''(r) - \left(\frac{2}{r} + \frac{d\ln\tilde{\rho}}{dr}\right)\,\mathcal{C}_n'(r)\right]W_{\ell mn} = 0 \ \ \text{and} \ \ \left[\mathcal{C}_n'(r) - \left(\frac{2}{r} + \frac{d\ln\tilde{\rho}}{dr}\right)\,\mathcal{C}_n(r)\right]Z_{\ell mn} = 0 \ .$$

We show the derivation for the somewhat simpler Boussinesq approximation which yields the condition

$$\frac{\partial}{\partial r} \frac{\boldsymbol{u}_H}{r} = 0$$

where the index H denotes the horizonal flow components. In terms of poloidal and toroidal components this implies

$$\frac{\partial}{\partial r} \frac{1}{r} \left(\nabla_H \frac{\partial W}{\partial r} \right) = \nabla_H \frac{1}{r} \left(\frac{\partial^2}{\partial r^2} - \frac{2}{r} \frac{\partial}{\partial r} \right) W = 0$$

and

$$\frac{\partial}{\partial r} \frac{1}{r} \nabla \times \mathbf{e}_r Z = \nabla \times \mathbf{e}_r \frac{1}{r} \left(\frac{\partial}{\partial r} - \frac{2}{r} \right) Z = 0$$

which can be fulfilled with

$$\left(\frac{\partial^2}{\partial r^2} - \frac{2}{r}\frac{\partial}{\partial r}\right)W = 0$$

and

$$\left(\frac{\partial}{\partial r} - \frac{2}{r}\right) Z = 0 \ .$$

In spectral representation this then reads

$$\left(\mathcal{C}_n'' - \frac{2}{r}\mathcal{C}_n'\right)W_{\ell mn} = 0 \ \text{ and } \ \left(\mathcal{C}_n' - \frac{2}{r}\mathcal{C}_n\right)Z_{\ell mn} = 0 \ .$$

4.7.2 Thermal boundary conditions

For Entropy or temperature in the Boussinesq approximation either fixed value of fixed flux conditions are used. The former implies

$$s = \text{const.}$$
 or $T = \text{const.}$

at r_i and/or r_o , while the latter means

$$\frac{\partial}{\partial r}s = \text{const.}$$
 or $\frac{\partial}{\partial r}T = \text{const.}$

In spectral representation for example the respective entropy condition read

$$C_n s_{\ell mn} = \text{const.}$$
 or $C'_n s_{\ell mn} = \text{const.}$

Appropriate constant values need to be chosen and are instrumental in driving the dynamo when flux conditions are imposed.

4.7.3 Boundary conditions for chemical composition

For the chemical composition, either the value or the flux is imposed at the boundaries. The former implies:

$$\xi = \text{const.}$$

at r_i and/or r_o , while the latter means

$$\frac{\partial}{\partial r}\xi = \text{const.}$$

In spectral representation, this then reads

$$C_n \xi_{\ell mn} = \text{const.}$$
 or $C'_n \xi_{\ell mn} = \text{const.}$

4.7.4 Magnetic boundary conditions and inner core

Three different magnetic boundary conditions are implemented in MagIC. The most simple one is the conceptual condition at the boundary to an infinite conductor. Surface current in this conductor will prevent the internally produced magnetic field from penetrating so that the field has to vanish at the boundary. The condition are thus the same as for a rigid flow (with boundaries at rest). We only provide the spectral representation here:

$$C_n(r)W_{\ell mn} = 0 \text{ at } r = r_i, r_o . \tag{4.47}$$

Note that the summation convention with respect to radial modes n is used again. The no-slip condition further requires that the horizontal flow components also have to vanish, provided the two boundaries are at rest. This condition is fulfilled for

$$C_n(r)g_{\ell mn} = 0$$
, $C'_n(r)g_{\ell mn} = 0$ and $C_n(r)h_{\ell mn} = 0$. (4.48)

More complex are the conditions to an electrical insulator. Here we actually use matching condition to a potential field condition that are formulated like boundary conditions. Since the electrical currents have to vanish in the insulator we have $\nabla \times \boldsymbol{B}$, which means that the magnetic field is a potential field $\boldsymbol{B}^I = -\boldsymbol{\nabla} V$ with $\Delta V = 0$. This Laplace equation implies a coupling between radial and horizontal derivatives which is best solved in spectral space. Two potential contributions have to be considered depending whether the field is produced above the interface radius r_{BC} or below. We distinguish these contributions with upper indices I for internal or below and E for external or above. The total potential then has the form:

$$V_{\ell m}(r) = r_{BC} V_{\ell m}^{I} \left(\frac{r_{BC}}{r}\right)^{\ell+1} + r_{BC} V_{\ell m}^{E} \left(\frac{r}{r_{BC}}\right)^{\ell}.$$

with the two spectral potential representations $V_{\ell m}^I$ and $V_{\ell m}^E$. This provides well defined radial derivative for both field contributions. For boundary r_o we have to use the first contribution and match the respective field as well as its radial derivative to the dynamo solution. The toroidal field cannot penetrate the insulator and thus simply vanishes which yields h=0 or

$$C_n h_{\ell mn} = 0$$

in spectral space. The poloidal field then has to match the potential field which implies

$$\nabla_H \frac{\partial}{\partial r} g = -\nabla_H V^I$$

for the horizontal components and

$$\frac{\nabla_H^2}{r^2}g = \frac{\partial}{\partial r}V^I$$

for the radial. In spectral space these condition can be reduce to

$$\mathcal{C}'_n(r)g_{\ell mn} = V^I_{lm}$$
 and $\frac{\ell(\ell+1)}{r^2}\mathcal{C}_ng_{\ell mn} = -\frac{\ell+1}{r}V^I_{lm}.$

Combining both allows to eliminate the potential and finally leads to the spectral condition used in MagIC:

$$\left(\mathcal{C'}_n(r_o) + \frac{\ell}{r_o}\mathcal{C}_n(r_o)\right)g_{\ell mn} = 0$$

Analogous consideration lead to the respective condition at the interface to an insulating inner core:

$$\left(\mathcal{C'}_n(r_i) - \frac{\ell+1}{r_i}\mathcal{C}_n(r_i)\right)g_{\ell mn} = 0.$$

If the inner core is modelled as an electrical conductor, a simplified dynamo equation has to be solved in which the fluid flow is replaced by the solid-body rotation of the inner core. The latter is described by a single toroidal flow mode $(\ell=1,m=0)$. The resulting nonlinear terms can be expressed by a simple spherical harmonic expansion, where the superscript I denotes values in the inner core and ω_I its differential rotation rate:

$$\int d\Omega Y_{\ell}^{m\star} e_{r} \cdot \left[\nabla \times \left(u^{I} \times B^{I} \right) \right] = -i \omega_{I} m \frac{\ell(\ell+1)}{r^{2}} g_{\ell m}^{I}(r) , \qquad (4.49)$$

$$\int d\Omega Y_{\ell}^{m\star} \mathbf{e}_{r} \cdot \left[\nabla \times \nabla \times \left(\mathbf{u}^{I} \times \mathbf{B}^{I} \right) \right] = -i \omega_{I} m \frac{\ell(\ell+1)}{r^{2}} h_{\ell m}^{I}(r) . \tag{4.50}$$

The expensive back and forth transformations between spherical harmonic and grid representations are therefore not required for advancing the inner-core magnetic field in time.

In the inner core the magnetic potentials are again conveniently expanded into Chebyshev polynomials. The Chebyshev variable x spans the whole diameter of the inner core, so that grid points are dense near the inner-core boundary but sparse in the center. The mapping is given by:

$$x(r) = \frac{r}{r_i} , -r_i \le r \le r_i .$$
 (4.51)

Each point in the inner core is thus represented twice, by grid points (r, θ, ϕ) and $(-r, \pi - \theta, \phi + \pi)$. Since both representations must be identical, this imposes a symmetry constraint that can be fulfilled when the radial expansion comprises only polynomials of even order:

$$g_{\ell m}^{I}(r) = \left(\frac{r}{r_i}\right)^{\ell+1} \sum_{i=0}^{M-1} g_{\ell m \, 2i}^{I} \, \mathcal{C}_{2i}(r) \ . \tag{4.52}$$

An equivalent expression holds for the toroidal potential in the inner core. FFTs can again by employed efficiently for the radial transformation, using the M extrema of $C_{2M-1}(r)$ with x > 0 as grid points.

The sets of spectral magnetic field equations for the inner and the outer core are coupled via continuity equations for the magnetic field and the horizontal electric field. Continuity of the magnetic field is assured by (i) continuity of the toroidal potential, (ii) continuity of the poloidal potential, and (iii) continuity of the radial derivative of the latter. Continuity of the horizontal electric field demands (iv) that the radial derivative of the toroidal potential is continuous, provided that the horizontal flow and the electrical conductivity are continuous at the interface. These four conditions replace the spectral equations (4.26), (4.27) on the outer-core side and equations (4.49), (4.50) on the inner-core side. Employing free-slip conditions or allowing for electrical conductivity differences between inner and outer core leads to more complicated and even non-linear matching conditions.

CHAPTER

FIVE

CONTRIBUTING TO THE CODE

MagIC is an open-source code, we thus value any possible contribution! There are several ways to directly contribute to the code:

Contribute

- **Do you want to contribute to the code?** Just clone the code and start modyfing it. Make sure that your modifications *don't alter the code*, try to *document your changes* as much as you can and follow the recommended *Fortran coding style*.
- Do you want to improve the documentation? Feel free to document some missing features. The documentation is stored in the directory \$MAGIC_HOME/doc/sphinx and relies on the documenting tool Sphinx. Some recommendations regarding documentation can be found *below*.
- Did you find a bug? Issues and feature requests should be raised in the github tracker.

5.1 Checking the consistency of the code

It is frequently required to check the consistency of the code, especially after the implementation of new features. For this reason, we developed the python test suite magic_wizard.py, located in the directory \$MAGIC_HOME/samples/, which tests the compilation of the code and it's results against a set of standard solutions in sample directories to check if the code produces the correct output.

You can run it as follows:

```
./magic_wizard.py <options>
```

It supports the following options:

```
--help
                    Show usage overview
--level LEV
                          Run only tests from level LEV
--use-debug-flags
                          Compile MagIC with the debug flags
--use-mpi
                          Use MPI
--use-openmp
                          Use the hybrid version of MagIC
--use-mkl
                          Use the MKL for FFTs and Lapack calls
--use-shtns
                         Use SHTns for Legendre transforms
--use-precond USE_PRECOND Use matrix preconditioning
--nranks NRANKS
                          Specify the number of MPI ranks
--nthreads NTHREADS
                          Specify the number of threads (hybrid version)
--mpicmd MPICMD
                          Specify the mpi executable (mpiexec, mpirun, srun)
```

Note: Make sure that your environment variables FC and CC are correctly defined otherwise the script will use the default system compilers.

The --level LEV option defines the priority level of check and validation of the code. It has the following levels of checking:

Level	Cases to check (subdirectories)		
0	 Boussinesq dynamo benchmark (Christensen et al., 2001) - start from zero (dynamo_benchmark) Variable transport properties (viscosity, thermal diffusivity and electrical diffusivity) in an anelastic convective model (varProps) Test of a case that uses finite differences - restart from a case that used Chebyshev polynomials (finite_differences) Boussinesq dynamo benchmark (Christensen et al., 2001) - start from a saturated state (boussBenchSat) Double-diffusive convection benchmark (Breuer et al., 2010) - start from a saturated state (doubleDiffusion) Axisymmetric spherical Couette flow - this auto-test checks the axisymmetric version of MagIC (couetteAxi) 		
1	 Test reading and writing of restart files (testRestart) Test different grid truncations (testTruncations) Test mapping on to a new grid (testMapping) Test different outputs produced (testOutputs) Test different radial outputs - *R.TAG (testRadialOutputs) 		
2	Hydrodynamic anelastic benchmark (Jones et al., 2011) (hydro_bench_anel)		
3	$ \begin{array}{cccccccccccccccccccccccccccccccccccc$		
4	 Test the writing of CMB and coeff files (testCoeffOutputs) Test the writing of RMS force balance (testRMSOutputs) Test the writing of Graphic and Movie files (testGraphMovieOutputs) Test the writing of TO and Geos outputs (testTOGeosOutputs) 		

5.2 Advices when contributing to the code

- Before committing your modifications always make sure that the auto-tests pass correctly.
- Try to follow the same coding style rules as in the rest of the code:
 - 1. Never use TABS but always SPACES instead
 - 2. Use 3 spaces for indentation

Note: These two rules can be easily set in your \$HOME/.vimrc file if you use vim:

```
au FileType fortran set shiftwidth=3
au FileType fortran set tabstop=3
au FileType fortran set expandtab
```

- 3. Never use capital letters for variable declaration or Fortran keywords
- 4. Never use dimension (len) for declaring array but rather real (cp) :: data(len)
- 5. Always use the default precisions when introducing new variables (cp)

These rules try to follow the general recommendations on modern fortran programming that can be found on www.fortran90.org or in the book Modern Fortran - style and usage by N. S. Clerman and W. Spector.

5.3 Building the documentation and contributing to it

The documentation is generated using Sphinx. To build it you'll thus need to install this python module on your machine. This is in general directly available on most of the Linux distributions under the name python-sphinx. Once installed, just go to the documentation directory

```
$ cd $MAGIC_HOME/doc/sphinx
```

and build the html documentation

```
$ make html
```

The complete documentation will then be built in a local directory named \$MAGIC_HOME/doc/sphinx/.build/html.

If LaTeX is installed on your work station, it is also possible to build the corresponding manual of the documentation in the pdf format:

```
$ make latexpdf
```

The resulting pdf is then generated in a local directory named $MAGIC_HOME/doc/sphinx/.build/latex$.

It is pretty straightforward to contribute to the documentation by simply adding some contents to the different rst files. Informations about reStructuredText syntax can be found on www.sphinx-doc.org, while helpful CheatSheet are accessible here or there.

CHAPTER

SIX

INPUT PARAMETERS

True runtime input parameters are read from STDIN as namelists, a Fortran feature. A namelist is identified by its unique name &name. The name-statement is followed by the parameters that are part of the namelist in the format parameter=value,. The namelist is closed by a backslash. The subroutine defaultNamelists (in the module Namelist.f90) defines a default value for each parameter. Only the parameters whose value should differ from its default have to be stated in the namelist.

An example for the short namelist defining inner core parameters is

```
&inner_core
  sigma_ratio = 1.0,
  nRotIc = 1
```

Comas can be used to seperate namelist entries since they are not interpreted by the code.

Magic uses the following eight namelists:

Namelists

- 1. & grid for resolution
- 2. &control for control parameters and numerical parameters.
- 3. &phys_param for the physical parameters.
- 4. &B_external for setting up an external field contribution
- 5. &start field to define the starting fields.
- 6. &output_control for defining the output.
- 7. &mantle for setting mantle parameters.
- 8. &inner_core for setting inner core parameters.

The number of possible input parameters has grown to more than 100/150. Don't be confused by all the possible options though, since all parameters are internally set to a useful default value!

Practically, in a production run, the number of parameters you may want to adjust is thus much smaller. As an example, the following namelist shows you how to initiate and quickly run one of the anelastic benchmarks by (Jones et al., 2011):

```
&grid

n_r_max = 97, ! 97 radial grid points

n_cheb_max = 95,

n_phi_tot = 288, ! 288 points in the azimuthal direction

n_r_ic_max = 17,
```

```
n_cheb_ic_max=15,
minc =1,
                          ! No azimuthal symmetry
&control
mode
           =1,
                          ! This is a non-magnetic case
tag ="test",
n_time_steps=50000,
                          ! Number of time steps
courfac =2.5D0,
alffac
           =1.000,

\begin{array}{ll}
\text{dtmax} & =1.0\text{DO}, \\
\text{=}1.0\text{D-4},
\end{array}

                          ! Maximum allowed time-step
n\_cour\_step = 5,
alpha = 0.6D0,
runHours =23,
runHours =23, ! Run time (hours)
runMinutes =30, ! Run time (minutes)
&phys_param
ra =1.48638035D5, ! Rayleigh number
ek
          =1.0D-3, ! Ekman number
pr
          =1.000,
                          ! Prandtl number
strat =5.D0,
polind =2.0D0,
                          ! Density contrast
                          ! Polytropic index
radratio =0.35D0,
                          ! Aspect ratio of the spherical shell
=0.D0,
                          ! Gravity profile
           =0.D0,
g1
           =1.D0,
g2
                          ! Entropy boundary condition
ktops
           =1,
kbots
           =1,
            =1,
                          ! Mechanical boundary condition
ktopv
kbotv
           =1,
&start_field
l_start_file=.false.,
start_file ="checkpoint_end.CJ3",
init_s1 =1919, ! Initial entropy perturbation pattern
amp_s1
           =0.01,
                          ! Amplitude of the initial perturbation
&output_control
n_log_step =50, ! Store time series every 50 time steps
n_graphs =1, ! 1 G_#.TAG file produced at the end of the run
n_specs
           =5,
                          ! 5 spectra produced during the run
n_rsts =1, !
runid ="C.Jones bench",
                          ! 1 checkpoint_end.TAG file produced at the end of the run
runid
&mantle
nRotMa
           = 0
&inner_core
sigma_ratio =0.d0,
                         ! Non-conducting inner core
nRotIC = 0,
```

This example might then be easily adapted to your desired configuration.

6.1 Grid namelist

This namelist defines the resolution of the computations. Keep in mind that **MagIC** is a 3D pseudo-spectral spherical shell code using Chebyshev polynomial expansions in the radial and spherical harmonic expansions in the angular directions.

6.1.1 Outer Core

• n_r_max (default n_r_max=33) is an integer which gives the number of grid points in the radial direction in the outer core ([r_i, r_o]). If Chebyshev polynomials are used for the radial integration scheme, there are some constraints on the value of n_r_max: first of all it must be of the form 4*n+1, where n is an integer; and second the prime decomposition of n_r_max-1 should only contain multiple of 3, 4 and 5 (this second condition comes from the limitations of the built-in discrete cosine transforms). This constraint is released when finite differences are used.

Note: If Chebyshev polynomials are used, the possible values for n_r_{max} below 220 are hence: 17, 21, 25, 33, 37, 41, 49, 61, 65, 73, 81, 97, 101, 109, 121, 129, 145, 161, 181, 193, 201, 217,...

- n_cheb_max (default n_cheb_max=31) is an integer which is the number of terms in the Chebyshev polynomial expansion to be used in the radial direction the highest degree of Chebyshev polynomial used being n_cheb_max-1. Note that n_cheb_max <= n_r_max. This quantity will not be used if finite differences are used.
- n_phi_tot (default n_phi_tot=192) is an integer which gives the number of longitudinal/azimuthal grid points. It has the following constraints:
 - n_phi_tot must be a multiple of minc (see below)
 - n_phi_tot/minc must be a multiple of 4
 - n_phi_tot must be a multiple of 16

Note: The possible values for n_phi_max are thus: 16, 32, 48, 64, 96, 128, 192, 256, 288? 320, 384, 400, 512, 576, 640, 768, 864, 1024, 1280, 1536, 1792, 2048, ...

- l_axi (default l_axi=.false.) is a logical. When set to true, one considers only the axisymmetric mode (i.e. MagIC becomes a 2-D axisymmetric code).
- n_theta_axi (default n_theta_axi=0) is an integer which gives the number of latitudinal grid points when MagIC computes only the axisymmetric mode.
- **fd_order** (default *fd_order=2*) is an integer. This is the order of the finite difference scheme for the bulk points (possible values are 2, 4, 6).
- **fd_order_bound** (default *fd_order_bound=2*) is an integer. This is the order of the finite difference scheme for the boundary points (possible values are 1,2,3,4,5,6,...).
- **fd_stretch** (default *fd_stretch=0.3*) is a real. It controls the ratio between the number of points in the boundary layers and in the bulk.
- fd_ratio (default fd_ratio=0.1) is a real. It controls the ratio between the smallest grid spacing and the largest grid spacing.

6.1. Grid namelist 47

Note: When *fd_ratio* is set to 1, the radial grid is regularly-spaced.

6.1.2 Inner Core

- n_r_{ic} max (default n_r_{ic} max=17) is an integer which gives the number of grid points in the radial direction in the inner core ([0, r_i]). It too, must be of the form 4*n+1, where n is an integer.
- n_cheb_ic_max (default n_cheb_ic_max=15) is the number of terms in the Chebyshev polynomial expansion in the radial direction in the inner core. Only Chebyshev polynomials of even degrees are used in the expansion giving the highest degree used to be 2*n_cheb_ic_max-2. Note that here too, n_cheb_ic_max <= n_r_max.

6.1.3 Symmetry and aliasing

- minc (default minc=1) is an integer which gives the longitudinal symmetry. e.g: minc=n would give an n-fold rotational symmetry in the azimuthal direction. One can use this to reduce computational costs when the symmetry of the solution is known. The orders of the spherical harmonic expansion (m) are multiples of minc.
- nalias (default nalias=20) is an integer which determines antialiasing used in the spherical harmonic representation. Note that 20 <= nalias <= 30.

The number of grid points in latitude $n_theta_max = n_phi_tot/2$. The maximum degree (1_max) and maximum order (m_max) of the spherical harmonic expansion are determined by nalias:

```
l_max = (nalias * n_theta_max)/30
```

6.2 Control namelist

This namelist defines the numerical parameters of the problem plus the variables that control and organize the run.

• mode (default mode=0) is an integer which controls the type of calculation performed.

mode=0	Self-consistent dynamo
mode=1	Convection
mode=2	Kinematic dynamo
mode=3	Magnetic decay modes
mode=4	Magneto convection
mode=5	Linear onset of convection
mode=6	Self-consistent dynamo, but with no Lorentz force
mode=7	Super-rotating inner core or mantle, no convection and no magnetic field
mode=8	Super-rotating inner core or mantle, no convection
mode=9	Super-rotating inner core or mantle, no convection and no Lorentz force
mode=10	Super-rotating inner core or mantle, no convection, no magnetic field, no Lorentz force and no
	advection

- tag (default tag="default") is a character string, used as an extension for all output files.
- n_time_steps (default n_time_steps=100) is an integer, the number of time steps to be performed.
- **tEND** (default *tEND=0.0*) is a real, which can be used to force the code to stop when :math:t=tEND. This is only used when t/=tEND.

• alpha (default alpha=0.5) is a real. This is the weight used for current time step in implicit time step.

6.2.1 Default scales

• n_tScale (default n_tScale=0) is an integer, which determines the time scaling

n_tScale=0	Use viscous time scale.	d^2/ν
n_tScale=1	Use magnetic time scale.	d^2/η
n_tScale=2	Use thermal time scale.	d^2/κ
n_tScale=3	Use rotational time scale.	Ω^{-1}

• n_lScale (default n_1Scale=0) is an integer which determines the reference length scale.

n_lScale=0	Use outer core.
n_lScale=1	Use total core.

• enscale (default enscale=1.0) is a real. This is the scaling for energies.

6.2.2 Update control

- l_update_v (default l_update_v=.true.) is a logical that specifies whether the velocity field should be time-stepped or not.
- l_update_b (default l_update_b=.true.) is a logical that specifies whether the magnetic field should be time-stepped or not.
- l_update_s (default l_update_s=.true.) is a logical that specifies whether the entropy/temperature should be time-stepped or not.

6.2.3 Time step control

A modified courant criteria including a modified Alfven-velocity is used to account for the magnetic field. The relative and absolute importance of flow and Alfven-velocity can be controlled by **courfac** and **alffac** respectively. The parameter **l_cour_alf_damp** allows to choose wheter the actual Alven speed is used to estimate the Courant condition or if damping (see Christensen et al., GJI, 1999) is included.

- **dtstart** (default dtstart=0.0) is a real, which is used as the initial time step if the starting solution is initialized (see below) and dtstart > 0.
- dtMax (default dtMax=1e-4) is a real. This is the maximum allowed time step δt . If $\delta t >$ dtmax, the time step is decreased to at least dtmax (See routine $dt_courant$). Run is stopped if $\delta t <$ dtmin and dtmin = 10^{-6} dtmax.
- courfac (default courfac=2.5) is a real used to scale velocity in courant criteria.
- alffac (default alffac=1.0) is a real, used to scale Alfven-velocity in courant criteria.
- l_cour_alf_damp (default l_cour_alf_damp=.true.) is a logical. This is used to decide whether the damping of the Alven waves is taken into account when estimating the Courant condition (see Christensen et al., GJI, 1999). At low Ekman numbers, this criterion might actually lead to spurious oscillations/instabilities of the code.
- n_cour_step (default n_cour_step=10) is an integer. This is the number of time steps before consecutive checking of courant criteria. Note: the courant criteria is checked always after the time step has been changed if n_cour_step>0.

6.2. Control namelist 49

6.2.4 Run time

The total desired runtime (in human units and not in CPU units) can be specified with the three variables **runHours**, **runMinutes** and **runSeconds**.

- runHours (default runHours=0) is an integer that controls the number of run hours.
- runMinutes (default runMinutes=0) is an integer that controls the .
- runSeconds (default runSeconds=0) is an integer that controls the number of run hours.

Here is an example for a run of 23h30:

```
runHours = 23,
runMinutes = 30,
```

6.2.5 Hyperdiffusivity

Hyperdiffusion can be applied by multiplying the diffusion operators by a factor of the form

$$d(\ell) = 1 + D \left[\frac{\ell + 1 - \ell_{hd}}{\ell_{max} + 1 - \ell_{hd}} \right]^{\beta}$$

for the spherical harmonic degrees $\ell \geq \ell_{hd}$.

- **difnu** (default difnu=0.0) is a real. This is the amplitude D of the viscous hyperdiffusion.
- difkappa (default difkappa=0.0) is a real. This is the amplitude D of the thermal hyperdiffusion.
- **difeta** (default difeta=0.0) is a real. This is the amplitude D of the magnetic hyperdiffusion.
- **Idif** (default 1 dif = 1) is an integer. This is the degree ℓ_{hd} where hyperdiffusion starts to act.
- **Idifexp** (default 1 difex p = -1) is an integer. This is the exponent β of hyperdiffusion.

6.2.6 Angular momentum correction

In case of the use of stress-free boundary conditions at both boundaries, it is safer to ensure that the angular momentum is correctly conserved. This can be enforced through the following input variables:

- l_correct_AMe (default l_correct_AMe=.false.) is a logical. This is used to correct the equatorial angular momentum.
- l_correct_AMz (default l_correct_AMz=.false.) is a logical. This is used to correct the axial angular momentum.

6.2.7 Radial scheme and mapping of the Gauss-Lobatto grid

In MagIC, one can either use finite differences or Chebyshev polynomials for the radial integration scheme. This choice is controlled by the following input parameter:

• radial_scheme (default radial_scheme='CHEB') is a character string.

radial_scheme='CHEB'	Use Chebyshev polynomials
radial_scheme='FD'	Use finite differences

When Chebyshev polynomials are used, it is also possible to use a non-linear mapping function to concentrate/diperse grid points around a point inside the domain.

- l_newmap (default l_newmap=.false.) is a logical. A radial mapping can be applied to the Chebyshev grid when l_newmap is set to .true.. The radial profile of the mapping function is then stored during the initialisation of the code in the file *rNM.TAG*.
- map_function (default map_function='arcsin') is a character string. This allows to select which mapping function is used:

map_function='TAN'	Use a tangent mapping (see Bayliss and Turkel 1992)
map_function='ARCSIN'	Use finite differences (see Kosloff and Tal-Ezer 1993)

If the tangent mapping is used, the function that re-distributes the collocation points is expressed by

$$r = \frac{1}{2} \left(\alpha_2 + \frac{\tan \left[\lambda (r_{cheb} - x_0) \right]}{\alpha_1} \right) + \frac{r_i + r_o}{2} ,$$

where the Gauss-Lobatto collocation points are

$$r_{cheb} = \cos\left(\frac{\pi(k-1)}{N_r}\right), \quad k = 1, 2, ..., n_r, \quad n_r = n_r max$$

and $r \in [r_i, r_o], r_{cheb} \in [-1.0, 1.0]$. The parameters to calculate r are

$$\lambda = \frac{\tan^{-1}(\alpha_1(1 - \alpha_2))}{1 - x_0}$$

$$x_0 = \frac{K - 1}{K + 1}$$

$$K = \frac{\tan^{-1}(\alpha_1(1 + \alpha_2))}{\tan^{-1}(\alpha_1(1 - \alpha_2))}.$$

The coefficient α_1 determines the degree of concentration/dispersion of the grid points around $r_{cheb} = \alpha_2$. If α_1 is too high, the r function becomes nearly discontinuous. To avoid numerical problems, α_1 should remain close to unity.

If the arcsin mapping is used, the function that re-distributes the collocation points is given by

$$r = \frac{1}{2} \left[\frac{\arcsin\left(\alpha_1 r_{cheb}\right)}{\arcsin\alpha_1} \right] + \frac{r_i + r_o}{2} ,$$

In the Kosloff and Tal-Ezer mapping, α_1 transforms the Gauss-Lobatto grid into a more regularly-spaced grid. When $\alpha_1 \to 0$ one recovers the Gauss-Lobatto grid, while $\alpha_1 \to 1$ yields a regular grid.

Warning: The Kosloff-Tal-Ezer mapping becomes singular when $\alpha_1=1$. Acceptable values are $0<\alpha_1<1$. Note that the error increases as $\epsilon=\left(\frac{1-\sqrt{1-\alpha_1^2}}{\alpha_1}\right)^{N_r}$.

- alph1 (default alph1=0.8) is a real. This is a control parameter of the mapping function.
- alph2 (default alph2=0.0) is a real. This is a control parameter of the mapping function.

6.2.8 Miscellaneous

• l_non_rot (default l_non_rot=.false.) is a logical. Use it when you want to do non-rotating numerical simulations.

6.2. Control namelist 51

• anelastic_flavour (default anelastic_flavour="None") is a character string. This allows to change the thermal diffusion operator used within the anelastic approximation. Possible values are:

anelastic_flavour='LBR'	Entropy diffusion
anelastic_flavour='ENT'	Entropy diffusion
anelastic_flavour='ALA'	Anelastic liquid approximation
anelastic_flavour='TDIFF'	Temperature diffusion
anelastic_flavour='TEMP'	Temperature diffusion

• **thermo_variable** (default thermo_variable="S") is a character string. This allows to change the default thermodynamic variable (and hence change the entropy/temperature equation used). This switch only matters when one wants to run an anelastic model. Possible values are:

thermo_variable='S'	Use entropy as a primitive variable
thermo_variable='T'	Use temperature as a primitive variable

• polo_flow_eq (default polo_flow_eq="WP") is a character string. This allows to change how the equation for the poloidal flow potential is constructed. One can either use the radial component of the Navier-Stokes equation and hence keep a coupled system that involve the poloidal potential W and the pressure p, or take the radial component of the double-curl of the Navier-Stokes equation to suppress pressure.

polo_flow_eq='WP'	Use the pressure formulation
polo_flow_eq='DC'	Use the double-curl formulation

6.3 Physical parameters namelist

This namelist contains all the appropriate relevant control physical parameters.

6.3.1 Dimensionless control parameters

• ra (default ra=0.0) is a real. This the thermal Rayleigh number expressed by

$$Ra = \frac{\alpha g_o \Delta T d^3}{\kappa \nu}$$

• raxi (default raxi=0. 0) is a real. This the compositional Rayleigh number expressed by

$$Ra_{\xi} = \frac{\alpha g_o \Delta \xi d^3}{\kappa_{\xi} \nu}$$

• ek (default ek=1e-3) is a real. This is the Ekman number expressed by

$$E = \frac{\nu}{\Omega d^2}$$

• **pr** (default pr=1.0) is a real. This is the Prandtl number expressed by

$$Pr = \frac{\nu}{\kappa}$$

• sc (default sc=10.0) is a real. This is the Schmidt number expressed by

$$Sc = \frac{\nu}{\kappa_{\xi}}$$

• prmag (default prmag=5.0) is a real. This is the magnetic Prandtl number expressed by

$$Pm = \frac{\nu}{\lambda}$$

• **po** (default $p \circ = 0$. 0) is a real. This is the Poincaré number expressed by

$$Po = \frac{\Omega_p}{\Omega}$$

- **prec_angle** (default *prec_angle=23.5*) is a real. This is the angle between the precession and the rotation axes expressed in degrees.
- **po_diff** (default po_diff=0.0) is a real. This is the Poincaré number in case of differential precession of core and mantle assuming both have the same rotation rate Ω and only the mantle is precessing.
- diff_prec_angle (default diff_prec_angle=23.5) is a real. This is the angle between the precession and the rotation axes expressed in degrees, for differential precession.
- radratio (default radratio=0.35) is a real. This is the ratio of the inner core radius r_i to the outer core radius r_o :

$$\eta = \frac{r_i}{r_o}$$

• strat (default strat=0.0) is a real. This is the number of density scale heights of the reference state:

$$N_{\rho} = \ln \frac{\tilde{\rho}(r_i)}{\tilde{\rho}(r_o)}$$

• **DissNb** (default *DissNb=0.0*) is a real. This is the dissipation number:

$$Di = \frac{\alpha_o g_o d}{c_p}$$

Warning: This can only be provided as a **replacement** input of **strat**. I.E., when one wants to define a reference state, one has to specify **either** strat **or** DissNb in the input namelist.

• **polind** (default polind=1.5) is a real. This is the polytropic index, which relates the background temperature to the background density:

$$\tilde{\rho} = \tilde{T}^m$$

Warning: Be careful: in its current version the code only handles **adiabatic** backgrounds, therefore changing polind physically means that the nature of the fluid (in particular its Grüneisen parameter) will change. For an ideal gas, it actually always follows $m+1=\frac{\gamma-1}{\gamma}$

• l_isothermal (default l_isothermal=.false.) is a logical. When set to .true., makes the temperature background isothermal (i.e. $\tilde{T}=cst.$). In that case, the dissipation number Di vanishes and there is no viscous and Ohmic heating left. The only difference with the Boussinesq set of equations are thus restricted to the density background $\tilde{\rho}$ and its radial derivatives that enters the viscous stress. This approximation is also called the zero Grüneisen parameter and was extensively explored by Denise Tortorella during her PhD.

6.3.2 Heat sources and sinks

• epsc0 (default epsc0=0.0) is a real. This is the volumetric heat source ϵ_0 that enters the thermal equilibrium relation:

$$-\nabla \cdot \left(\tilde{\rho}\tilde{T}\nabla s\right) + \epsilon_0 f(r) = 0 \tag{6.1}$$

The radial function f(r) can be modified with the variable nVarEps that enters the same input namelist.

• epscxi0 (default epscxi0=0.0) is a real. This is the volumetric source ϵ_{ξ} that enters the compositional equilibrium relation:

$$-\nabla \cdot (\tilde{\rho}\nabla\xi) + \epsilon_{\xi} = 0 \tag{6.2}$$

• **nVarEps** (default nVarEps=0) is an integer. This is used to modify the radial-dependence of the volumetric heat source, i.e. f(r) that enters equation (6.1).

nVarEps=0	Constant, i.e. $f(r) = \text{cst.}$.
nVarEps=1	Proportional to density, i.e. $f(r) = \tilde{\rho}(r)$.
nVarEps=2	Proportional to density times temperature, i.e. $f(r) = \tilde{\rho}(r)\tilde{T}$.

6.3.3 Realistic interior models

• interior_model (default interior_model="None") is a character string. This defines a polynomial fit of
the density profile of the interior structure of several astrophysical objects. Possible options are "earth",
"jupiter", "saturn" and "sun" (the naming is not case sensitive).

Warning: When interior_model is defined the variables strat, polind, g0, g1 and g2 are not interpreted.

The subroutine radial gives the exact details of the implementation.

r_cut_model (default r_cut_model=0.98) is a real. This defines the cut-off radius of the reference model,
 i.e. the fluid domain is restricted to radii with r ≤ r_{cut}.

The following input parameters will thus define a polynomial fit to the expected interior structure of Jupiter until 99% of Jupiter's radius (assumed here at the 1 bar level)

```
interior_model="JUP",
r_cut_model =0.99e0,
```

6.3.4 Gravity

The radial dependence of the gravity profile can be adjusted following

$$g(r) = g_0 + g_1 \frac{r}{r_o} + g_2 \left(\frac{r_o}{r}\right)^2 \tag{6.3}$$

The three following parameters are used to set this profile

- g0 (default g0=0) is the pre-factor of the constant part of the gravity profile, i.e. g_0 in equation (6.3).
- g1 (default g1=1) is the pre-factor of the linear part of the gravity profile, i.e. g_1 in equation (6.3).
- **g2** (default g2=0) is the pre-factor of the $1/r^2$ part of the gravity profile, i.e. g_2 in equation (6.3).

6.3.5 Transport properties

• **difExp** (default difExp=-0.5) is a real. This is the exponent that is used when nVarVisc=2, nVarDiff=2 or nVarCond=4.

Electrical conductivity

There are several electrical conductivity profiles implemented in the code that can be chosen with the nVarCond input variable. The following one corresponds to a constant electrical conductivity in the deep interior $(r < r_m)$ and an exponential decay in the outer layer.

$$\sigma(r) = 1 + (\sigma_m - 1) \left(\frac{r - r_i}{r_m - r_i}\right)^a \quad \text{for} \quad r < r_m,$$

$$\sigma(r) = \sigma_m \exp\left[a\left(\frac{r - r_m}{r_m - r_i}\right) \frac{\sigma_m - 1}{\sigma_m}\right] \quad \text{for} \quad r \ge r_m.$$
(6.4)

• **nVarCond** (default *nVarCond=0*) is an integer. This is used to modify the radial-dependence of the electrical conductivity.

nVarCond=0	Constant electrical conductivity, i.e. $\sigma = \text{cst.}$
nVarCond=1	$\sigma \propto \tanh[a(r-r_m)]$
nVarCond=2	See equation (6.4).
nVarCond=3	Magnetic diffusivity proportional to $1/\tilde{\rho}$, i.e.
	$\lambda = rac{ ilde{ ho}_i}{ ilde{ ho}}$
nVarCond=4	Radial profile of the form:
	$\lambda = \left(\frac{\tilde{\rho}(r)}{\tilde{\rho}_i}\right)^{\alpha}$

- con_RadRatio (default $con_RadRatio=0.75$) is a real. This defines the transition radius r_m that enters equation (6.4).
- con_DecRate (default con_DecRate=9) is an integer. This defines the decay rate a that enters equation (6.4).
- con_LambdaMatch (default $con_LambdaMatch=0.6$) is a real. This is the value of the conductivity at the transition point σ_m that enters equation (6.4).
- con_LambdaOut (default con_LambdaOut=0.1) is a real. This is the value of the conduvity at the outer boundary. This parameter is only used when nVarCond=1.
- con_FuncWidth (default con_FuncWidth=0.25) is a real. This parameter is only used when nVarCond=1.
- r_LCR (default $r_LCR=2.0$) is a real. r_LCR possibly defines a low-conductivity region for $r \ge r_{LCR}$, in which the electrical conductivity vanishes, i.e. $\lambda = 0$.

Thermal diffusivity

• **nVarDiff** (default *nVarDiff=0*) is an integer. This is used to change the radial-dependence of the thermal diffusivity:

nVarDiff=0	Constant thermal diffusivity κ
nVarDiff=1	Constant thermal conductivity, i.e.
	$\kappa = rac{ ilde{ ho}_i}{ ilde{ ho}(r)}$
nVarDiff=2	Radial profile of the form:
	$\kappa = \left(\frac{ ilde{ ho}(r)}{ ilde{ ho}_i} ight)^{lpha}$
nVarDiff=3	polynomial-fit to an interior model of Jupiter
nVarDiff=4	polynomial-fit to an interior model of the Earth liquid
	core

Viscosity

• **nVarVisc** (default *nVarVisc=0*) is an integer. This is used to change the radial-dependence of the viscosity:

nVarVisc=0	Constant kinematic viscosity ν
nVarVisc=1	Constant dynamic viscosity, i.e.
	$ u = rac{ ilde{ ho}_o}{ ilde{ ho}(r)}$
nVarVisc=2	Radial profile of the form:
	$\nu = \left(\frac{\tilde{\rho}(r)}{\tilde{\rho}_i}\right)^{\alpha}$

where α is an exponent set by the namelist input variable difExp.

6.3.6 Anelastic liquid equations

Warning: This part is still work in progress. The input parameters here are likely to be changed in the future.

• **epsS** (default epsS=0.0) is a real. It controls the deviation to the adiabat. It can be related to the small parameter ϵ :

$$\epsilon \simeq \frac{\Delta T}{T} \simeq \frac{\Delta s}{c_p}$$

• cmbHflux (default cmbHflux=0.0) is a real. This is the CMB heat flux that enters the calculation of the reference state of the liquid core of the Earth, when the anelastic liquid approximation is employed.

• **slopeStrat** (default slopeStrat=20.0) is a real. This parameter controls the transition between the convective layer and the stably-stratified layer below the CMB.

6.3.7 Boundary conditions

Thermal boundary conditions

• **ktops** (default *ktops=1*) is an integer to specify the outer boundary entropy (or temperature) boundary condition:

ktops=1	Fixed entropy at outer boundary: $s(r_o) = s_{top}$
ktops=2	Fixed entropy flux at outer boundary: $\partial s(r_o)/\partial r = q_t$
ktops=3	Fixed temperature at outer boundary: $T(r_o) = T_{top}$
ktops=4	Fixed temperature flux at outer boundary: $\partial T(r_o)/\partial r = q_t$

- **kbots** (default *ktops=1*) is an integer to specify the inner boundary entropy (or temperature) boundary condition.
- s_top (default $s_top=0 0 0.0 0.0$) is a real array of lateraly varying outer heat boundary conditions. Each four consecutive numbers are interpreted as follows:
 - 1. Spherical harmonic degree ℓ
 - 2. Spherical harmonic order m
 - 3. Real amplitude (cos contribution)
 - 4. Imaginary amplitude (sin contribution)

For example, if the boundary condition should be a combination of an $(\ell=1, m=0)$ sherical harmonic with the amplitude 1 and an $(\ell=2, m=1)$ spherical harmonic with the amplitude (0.5,0.5) the respective namelist entry could read:

```
s_top = 1, 0, 1.0, 0.0, 2, 1, 0.5, 0.5, ! The comas could be left away.
```

- s_bot (default $s_bot=0 \ 0 \ 0.0 \ 0.0$) is a real array. This is the same as s_top but for the bottom boundary.
- impS (default impS=0) is an integer. This is a flag to indicate if there is a localized entropy disturbance, imposed at the CMB. The number of these input boundary conditions is stored in n_impS (the maximum allowed is 20), and it's given by the number of sCMB defined in the same namelist. The default value of impS is zero (no entropy disturbance). If it is set in the namelist for an integer greater than zero, then sCMB has to be also defined in the namelist, as shown below.
- sCMB (default sCMB=0.0 0.0 0.0 0.0) is a real array of CMB heat boundary conditions (similar to the case of s_bot and s_top). Each four consecutive numbers are interpreted as follows:
 - 1. Highest amplitude value of the entropy boundary condition, stored in array peakS(20). When impS<0, peakS is a relative amplitude in comparison to the $(\ell=0,m=0)$ contribution (for example, the case s_top= 0 0 -1 0).
 - 2. θ coordinate (input has to be given in degrees), stored in array thetaS (20).
 - 3. ϕ coordinate (input has to be given in degrees), stored in array phis (20).
 - 4. Angular width (input has to be given in degrees), stored in array widthS (20).

Boundary conditions for chemical composition

ktopxi (default ktopxi=1) is an integer to specify the outer boundary chemical composition boundary condition:

ktopxi=1	Fixed composition at outer boundary: $\xi(r_o) = \xi_{top}$
ktopxi=2	Fixed composition flux at outer boundary: $\partial \xi(r_o)/\partial r = q_t$

- kbotxi (default ktopxi=1) is an integer to specify the inner boundary chemical composition boundary condition.
- **xi_top** (default $xi_top = 0 \ 0 \ 0.0 \ 0.0$) is a real array of lateraly varying outer chemical composition boundary conditions. Each four consecutive numbers are interpreted as follows:
 - 1. Spherical harmonic degree ℓ
 - 2. Spherical harmonic order m
 - 3. Real amplitude (cos contribution)
 - 4. Imaginary amplitude (sin contribution)

For example, if the boundary condition should be a combination of an $(\ell=1,m=0)$ sherical harmonic with the amplitude 1 and an $(\ell=2,m=1)$ spherical harmonic with the amplitude (0.5,0.5) the respective namelist entry could read:

```
xi_top = 1, 0, 1.0, 0.0, 2, 1, 0.5, 0.5, ! The comas could be left away.
```

- xi_bot (default xi_bot=0 0 0.0 0.0) is a real array. This is the same as xi_top but for the bottom boundary.
- **impXi** (default *impXi=0*) is an integer. This is a flag to indicate if there is a localized chemical composition disturbance, imposed at the CMB. The number of these input boundary conditions is stored in n_impXi (the maximum allowed is 20), and it's given by the number of xiCMB defined in the same namelist. The default value of impXi is zero (no chemical composiiton disturbance). If it is set in the namelist for an integer greater than zero, then xiCMB has to be also defined in the namelist, as shown below.
- xiCMB (default xiCMB=0.0 0.0 0.0 0.0) is a real array of CMB chemical composition boundary conditions (similar to the case of xi_bot and xi_top). Each four consecutive numbers are interpreted as follows:
 - 1. Highest amplitude value of the chemical composition boundary condition, stored in the array peakXi(20). When impXi<0, peakXi is a relative amplitude in comparison to the $(\ell=0,m=0)$ contribution (for example, the case xi_top= 0 0 -1 0).
 - 2. θ coordinate (input has to be given in degrees), stored in array thetaXi (20).
 - 3. ϕ coordinate (input has to be given in degrees), stored in array phiXi (20).
 - 4. Angular width (input has to be given in degrees), stored in array widthXi (20).

Mechanical boundary conditions

• **ktopy** (default ktopv=2) is an integer, which corresponds to the mechanical boundary condition for $r=r_0$.

ktopv=1	Stress-free outer boundary for $r=r_o$:
	$W_{\ell m}(r=r_o) = 0, \frac{\partial}{\partial r} \left(\frac{1}{r^2 \tilde{\rho}} \frac{\partial W_{\ell m}}{\partial r} \right) = 0$
	$\frac{\partial}{\partial r} \left(\frac{1}{r^2 \tilde{\rho}} Z_{\ell m} \right) = 0$
ktopv=2	Rigid outer boundary for $r = r_o$:
	$W_{\ell m} = 0, \frac{\partial W_{\ell m}}{\partial r} = 0,$
	$Z_{\ell m} = 0$

• **kbotv** (default kbotv=2) is an integer, which corresponds to the mechanical boundary condition for $r=r_i$.

Magnetic boundary conditions

• **ktopb** (default ktopb=1) is an integer, which corresponds to the magnetic boundary condition for $r=r_o$.

ktopb=1	Insulating outer boundary:
	$\frac{\partial g_{\ell m}}{\partial r} + \frac{\ell}{r} g_{\ell m} = 0, \frac{\partial h_{\ell m}}{\partial r} = 0$
ktopb=3	Finitely conducting mantle
ktopb=4	Pseudo-vacuum outer boundary:
	$\frac{\partial g_{\ell m}}{\partial r} = 0, h_{\ell m} = 0$

• **kbotb** (default kbotb=1) is an integer, which corresponds to the magnetic boundary condition for $r=r_i$.

kbotb=1	Insulating inner boundary:
	$\frac{\partial g_{\ell m}}{\partial r} - \frac{\ell + 1}{r} g_{\ell m} = 0, \frac{\partial h_{\ell m}}{\partial r} = 0$
kbotb=2	Perfectly-conducting inner core:
	$g_{\ell m} = \frac{\partial g_{\ell m}}{\partial r} = 0, \frac{\partial h_{\ell m}}{\partial r} = 0$
kbotb=3	Finitely conducting inner core
kbotb=4	Pseudo-vacuum outer boundary:
	$\frac{\partial g_{\ell m}}{\partial r} = 0, h_{\ell m} = 0$

Boundary condition for spherically-symmetric pressure

• **ktopp** (default ktopp=1) is an integer, which corresponds to the boundary condition for the spherically-symmetric pressure at $r=r_o$.

ktopp=1	The integral of the spherically-symmetric density perturbation vanishes.	
ktopp=2	The spherically-symmetric pressure fluctuation vanishes at the outer boundary.	

6.4 External Magnetic Field Namelist

The namelist &B_external provides options for imposing an external magnetic field.

6.4.1 Externally imposed magnetic field

• **n_imp** (default $n_i = 0$) is an integer controlling the type of external field applied.

n_imp=0	No external magnetic field
n_imp=1	Follows idea of Uli Christensen of external field compensating internal field such that
	radial component of magnetic field vanishes at $r/r_{cmb} = rrMP$ where rrMP is the
	'magnetopause radius' input by the user (see below)
n_imp=2	Uniform axisymmetric magnetic field of geometry given by 1_imp (see below)
n_imp=3	Uniform axisymmetric magnetic field which changes direction according to the direc-
	tion of the axial dipole of the internal magnetic field
n_imp=4	Same as n_imp=3 but the amplitude of the external field is scaled to the amplitude
	of the axial dipole of the internal field
n_imp=7	External field depends on internal axial dipole through Special Heyner feedback func-
	tions

- rrMP (default rrMP = 0.0) is a real which gives the value of 'magnetopause radius'. In other words, it gives the radius (as a fraction of r_cmb) at which the radial component of the magnetic field vanishes due to cancelling out of external and internal magnetic field components. Used only when n_imp = 1.
- amp imp (default amp imp = 0.0) is a real which gives the amplitude of the external magnetic field.
- **expo_imp** (default <code>expo_imp = 0.0</code>) is a real which gives the exponent of dependence of external magnetic field on the axial dipole of the internal magnetic field. Used for <code>n_imp=7</code>.
- bmax_imp (default $bmax_imp = 0.0$) is a real which gives the location of the maximum of the ratio of the poloidal potentials g_{ext}/g_{int} .
- l_imp (default l_imp = 1) is an integer which gives the geometry (degree of spherical harmonic) of the external magnetic field. The external field is always axisymmetric, hence m = 0 always. This option is used when n_imp = 2, 3 or 4.

6.4.2 Current carrying loop

To simulate experiments, an external current carrying loop, concentric to the sphere and in the equatorial plane, has been implemented in the code. It's radius is fixed at a distance $a=r_{cmb}/0.8$ to match conditions of the Maryland 3 metre experiment.

• l_curr (default l_curr = .false.) is a logical that controls switching on or off of the current carrying loop.

• amp_curr (default amp_curr = 0.0) is a real that gives the amplitude of magnetic field produced by the current carring loop.

Warning: Note that an external magnetic field is incompatible with a region of low conductivity inside the spherical shell (i.e, if $r_LCR < r_cmb$). Thus, while imposing an external magnetic field, make sure $r_LCR > r_cmb$ (which is the default case). For details on r_LCR , have a look at the section on *electrical conductivity* in the namelist for *physical parameters*.

6.5 Start field namelist

This namelist controls whether a start field from a previous solution should be used, or a specific field should be initialized.

6.5.1 Reading an input file of start fields

- l_start_file (default l_start_file=.false.) is a logical that controls whether the code should to read a file named start_file or not.
- start_file (default start_file="no_start_file") is a character string. This is the name of the restart file.
- **inform** (default *inform=-1*) is an integer that can be used to specify the format of start_file. This ensures possible backward compatibility with previous versions of the code. You shouldn't change this value except to read very old *checkpoint_end.TAG* files generated by older versions of MagIC.

inform=0	Oldest format used by U. Christensen
inform=1	Newer format used by U. Christensen
inform=2	Inner core introduced by J. Wicht
inform=-1	Default format

- scale_s (default scale_s=1.0) is a real. It can be possibly used to multiply the input entropy field from start_file by a constant factor scale_s.
- scale_xi (default scale_xi=1.0) is a real. It can be possibly used to multiply the input chemical composition field from start_file by a constant factor scale_xi.
- scale_v (default scale_v=1.0) is a real. It can be possibly used to multiply the input velocity field from start_file by a constant factor scale_v.
- scale_b (default scale_b=1.0) is a real. It can be possibly used to multiply the input magnetic field from start_file by a constant factor scale_b.
- tipdipole (default tipdipole=0.0) is a real that can be used to add non-axisymmetric disturbances to a start solution if non-axisymmetric parts have been lost due to mapping to a different symmetry. A $(\ell=1, m=1)$ entropy term is added with:

$$s_{10}(r) = \text{tipdipole } \sin[\pi(r - r_i)]$$

If a magnetic field without an m=1 term is mapped into a field that permits this term, the code adds the respective poloidal field using the $(\ell=1, m=0)$ poloidal magnetic field and scaling it with tipdipole.

• l_reset_t (default l_reset_t=.false.) is a logical that can be set to .true. in case one wants to reset the time of start file to zero.

6.5. Start field namelist

6.5.2 Defining the starting conditions

Initialisation of entropy

The heat equation with possible heat sources and sinks given by $epsc\theta$ is solved for the spherically-symmetric term $(\ell=0,m=0)$ to get its radial dependence. In addition to this initial state, two other laterally varying terms can be initialized. Their radial dependence are assumed to follow:

$$s(r) = 1 - 2x^2 + 3x^4 - x^6,$$

where

$$x = 2r - r_o - r_i.$$

The initial perturbation is thus set to zero at both boundaries r_i and r_o , and reaches its maximum amplitude of amp_s1 or amp_s2 at the mid-shell radius $r_i + 1/2$.

- init_s1 (default init_s1=0) is an integer that controls the initial entropy. The following values are possible:
 - init_s1=0: nothing is initialized
 - init_s1<100: a random-noise of amplitude amp_s1 is initialised. The subroutine initS in init_fields.f90 gives the detail of this implementation.
 - init_s1>100: initialisation of mode with the spherical harmonic order m given by the last two (or three) digits of init_s1 and the spherical harmonic degree ℓ given by the first two (or three) digits. Here are two examples:

```
init_s1 = 0707,
amp_s1 = 0.05,
```

will introduce a perturbation on the mode ($\ell = 7, m = 7$) with an amplitude of 0.05.

```
init_s1 = 121121,
amp_s1 = 0.01,
```

will introduce a perturbation on the mode ($\ell = 121, m = 121$) with an amplitude of 0.01.

- amp_s1 (default amp_s1=0.0) is a real used to contol the amplitude of the perturbation defined by init_s1.
- init_s2 (default init_s2=0) is an integer that controls a second spherical harmonic degee. It follows the same specifications as init_s1.
- amp_s2 (default amp_s2=0.0) is a real used to contol the amplitude of the perturbation defined by init_s2.

Initialisation of chemical composition

The chemical composition equation with possible volumetric sources and sinks given by epscxi0 is solved for the spherically-symmetric term ($\ell=0, m=0$) to get its radial dependence. In addition to this initial state, two other laterally varying terms can be initialized. Their radial dependence are assumed to follow:

$$\xi(r) = 1 - 2x^2 + 3x^4 - x^6,$$

where

$$x = 2r - r_o - r_i.$$

The initial perturbation is thus set to zero at both boundaries r_i and r_o , and reaches its maximum amplitude of amp_xi1 or amp_xi2 at the mid-shell radius $r_i + 1/2$.

- init_xi1 (default init_xi1=0) is an integer that controls the initial chemical composition. It follows the same specifications as init_s1.
- amp_xi1 (default amp_xi1=0.0) is a real used to contol the amplitude of the perturbation defined by init_xi1.
- init_xi2 (default init_xi2=0) is an integer that controls a second spherical harmonic degee. It follows the same specifications as init_s1.
- amp_xi2 (default amp_xi2=0.0) is a real used to contol the amplitude of the perturbation defined by init_xi2.

Initialisation of magnetic field

- init_b1 (default init_b1=0) is an integer that controls the initial magnetic field. The following values are possible:
 - init_b1<0: random noise initialization of all (ℓ, m) modes, except for $(\ell = 0, m = 0)$. The subroutine initB in the file init_fields.f90 contains the details of the implementation.
 - init_b1=0: nothing is initialized
 - init_b1=1: diffusive toroidal field initialized. Mode determined by imageon.
 - init_b1=2: $(\ell=1, m=0)$ toroidal field with a maximum field strength of amp_b1. The radial dependence is defined, such that the field vanishes at both the inner and outer boundaries. In case of an insulating inner core: $h(r) \approx r \sin[\phi(r-r_o)]$. In case of a conducting inner core: $h(r) \approx r \sin[\pi(r/r_o)]$.
 - init_b1=3: $(\ell=1,m=0)$ poloidal field whose field strength is amp_b1 at $r=r_i$. The radial dependence is chosen such that the current density j is independent of r:, i.e. $\partial j/\partial r=0$. $(\ell=2,m=0)$ toroidal field with maximum strength amp_b1.
 - init_b1=4: $(\ell = 1, m = 0)$ poloidal field as if the core were an insulator (potential field). Field strength at $r = r_i$ is again given by amp_b1.
 - init_b1=5: $(\ell = 1, m = 0)$ poloidal field with field strength amp_b1 at $r = r_i$. The radial dependence is again defined by $\partial j/\partial r = 0$.
 - init_b1=6: $(\ell=1, m=0)$ poloidal field independend of r.
 - init_b1=7: $(\ell=1,m=0)$ poloidal field which fulfills symmetry condition in inner core: $g(r) \approx \left(\frac{r}{r_i}\right)^2 \left[1-\frac{3}{5}\left(\frac{r}{r_o}\right)^2\right]$. The field strength is given by amp_b1 at $r=r_o$.
 - init_b1=8: same poloidal field as for init_b1=7. The toroidal field fulfills symmetry conditions in inner core and has a field strength of amp_b1 at $r=r_i$: $h(r) \approx \left(\frac{r}{r_i}\right)^3 \left\lceil 1-\left(\frac{r}{r_o}\right)^2 \right\rceil$.
 - init_b1=9: $(\ell=2, m=0)$ poloidal field, which is a potential field at the outer boundary.
 - init_b1=10: equatorial dipole only.
 - init_b1=11: axial and equatorial dipoles.
 - init_b1=21: toroidal field created by inner core rotation, equatorially symmetric ($\ell=1, m=0$): $h(r)=\text{ampb1}\left(\frac{r_i}{r}\right)^6$. The field strength is given by amp_b1 at $r=r_i$.
 - init_b1=22: toroidal field created by inner core rotation, equatorially antisymmetric ($\ell=2, m=0$). Same radial function as for init_b1=21.
- amp_b1 (default amp_b1=0.0) is a real used to contol the amplitude of the function defined by init_b1.

- **imagcon** (default *imagcon=0*) is an integer, which determines the imposed magnetic field for magnetoconvection. The magnetic field is imposed at boundaries.
 - imagcon=0: no magneto-convection
 - imageon<0: axial poloidal dipole imposed at ICB with a maximum magnetic field strength amp_b1.
 - imagcon=10: $(\ell=2, m=0)$ toroidal field imposed at ICB and CMB with a maximum amplitude amp b1 at both boundaries.
 - imagcon=11: same as imagcon=10 but the maximum amplitude is now amp_b1 at the ICB and -amp_b1 at the CMB.
 - imageon=12: $(\ell=1, m=0)$ toroidal field with a maximum amplitude of amp_b1 at the ICB and the CMB.
- **tmagcon** (tmagcon=0.0) is a real.

Initialisation of velocity field

- init_v1 (default $init_v1=0$) is an integer that controls the initial velocity. The following values are possible:
 - init_v1=0: nothing is initialized
 - init_v1=1: a differential rotation profile of the form

$$\Omega = \Omega_{ma} + 0.5\Omega_{ic} \quad \text{for} \quad s \le r_i$$

$$\Omega = \Omega_{ma} \quad \text{for} \quad s > r_i$$

where $s=r\sin\theta$ is the cylindrical radius. This profile only makes sense when one studies spherical Couette flows.

- init_v1=2: a differential rotation profile of the form $\Omega = \frac{\text{ampv1}}{\sqrt{1+s^4}}$ is introduced.
- init_v1>2: a random-noise of amplitude amp_v1 is initialised. The subroutine initV in init_fields.f90 gives the detail of this implementation.
- amp v1 (default amp v1=0.0) is a real used to contol the amplitude of the function defined by init v1.

6.6 Output control namelist

This namelist contains all the parameters that can be adjusted to control the outputs and diagnostics calculated by the code.

There are four different ways to control at which time step a specific output should be written. Outputs are generally distributed over the total calculation interval unless an output time interval is defined by a start time t_start and a stop time t_stop. If no t_start is provided, the start time of the calculation is used. If no t_stop is provided or t_stop>t_start the total calculation interval is assumed

1. **Prescribed number of outputs**. The outputs are distributed evenly over the total calculation interval so that the number of timesteps between two outputs is always the same, with the possible exception of the first interval. Last output is written for the last time step, and to compensate the interval before the first output may be longer. However, if t_stop is provided, the outputs are distributed evenly over the interval [t_stop, t_start] with equal times intervals between them.

Note: These input variables are usually named with a pattern that follows $n_{\text{outputName}}$, for instance, n_{graphs} , n_{rsts} , n_{specs} , n_{logs} , etc.

In case you want to make use of a specific time interval, the input variables follow a pattern of the form t_outputName_start, t_outputName_stop. For instance, t_graph_start, t_graph_stop, t_log_start, t_log_stop, t_spec_start, t_spec_stop, etc.

2. **User-defined interval between two outputs, given in number of time steps**. Again the last output is performed at the end of the run and a compensation may take place at the beginning.

Note: These input variables are usually named with a pattern that follows n_outputName_step, for instance, n_graph_step, n_rst_step, n_spec_step, n_log_step, n_movie_step, etc.

3. Defined time interval between two outputs.

Note: These input variables are usually named with a pattern that follows dt_outputName, for instance, dt_graph , dt_rst , dt_spec , dt_log , dt_movie , etc.

4. **User-defined times for output**. By default 5000 different times can be defined for each output type. This can be increased by increasing n_time_hits in the file output_data.f90. While the first three possibilities can only be used alternatively, the fourth one can be employed in addition to one of the two others.

Note: These input variables are usually named with a pattern that follows $t_{outputName}$, for instance, t_{graph} , t_{rst} , t_{spec} , t_{log} , t_{movie} , etc.

An important parameter in this context is <code>l_true_time</code>. If this is set to <code>.true.</code>, the time steps of the program are modified to meet a desired output time. This forces a recalculation of the inversion matricies and therefore requires some additional computing time. When <code>l_true_time=.false.</code>, the values at the timestep closest to the desired output time are chosen. Since the timesteps are generally small, this option suffices for most applications.

• l_true_time (default l_true_time=.false.) is a logical. It causes the code to change time steps to exactly meet the requested output times.

The different possible outputs control parameters are then extensively described in the following pages:

Possible outputs

- 1. Control standard/common outputs
- 2. CMB and radial coefficients
- 3. Storage of potentials in spectral space
- 4. Torsional oscillations diagnostics
- 5. Additional possible diagnostics

6.6.1 Standard time-series outputs

The **log** outputs controls the output of all the default time series of the file: kinetic and magnetic energies (*e_kin.TAG*, *e_mag_oc.TAG* and *e_mag_ic.TAG* files), dipole information (*dipole.TAG* file), rotation (*rot.TAG*) parameters (*par.TAG*) and various additional diagnostics (*heat.TAG*):

• $n_{\log step}$ (default $n_{\log step} = 50$) is an integer. This is the number of timesteps between two log outputs.

Warning: Be careful: when using too small n_log_step , the disk access will dramatically increases, thus decreasing the code performance.

- \mathbf{n} _logs (default n_10qs=0) is an integer. This is the number of log-information sets to be written.
- t_log (default t_log=-1.0 -1.0 ...) is real array, which contains the times when log outputs are requested.
- **dt_log** (default $dt_log=0.0$) is a real, which defines the time interval between log outputs.
- t_{log_start} (default $t_{log_start} = 0.0$) is a real, which defines the time to start writing log outputs.
- $t_{\log_{100}}$ (default $t_{\log_{100}}$ outputs. 0) is a real, which defines the time to stop writing log outputs.

6.6.2 Restart files

The **rst** outputs controls the output of restart files (*checkpoint_t_#.TAG*) (i.e. check points in time from which the code could be restarted):

- n_rst_step (default n_rst_step=0) is an integer. This is the number of timesteps between two restart files.
- n_rsts (default n_rsts=1) is an integer. This is the number of restart files to be written.
- t_rst (default t_rst=-1.0 -1.0 ...) is real array, which contains the times when restart files are requested.
- **dt_rst** (default \(dt_rst = 0 \cdot 0 \) is a real, which defines the time interval between restart files.
- t_rst_start (default t_rst_start=0.0) is a real, which defines the time to start writing restart files.
- t_rst_stop (default t_rst_stop=0.0) is a real, which defines the time to stop writing restart files.
- n_stores (default n_stores=0) is an integer. This is another way of requesting a certain number of restart files. However, instead of creating each time a new restart file, if n_stores > n_rsts the restart file is overwritten, which can possibly help saving some disk space.

Warning: The rst files can become quite big and writting them too frequently will slow down the code. Except for very special use, the default set up should be sufficient.

6.6.3 Graphic files

The **graph** outputs controls the output of graphic files $(G_\#.TAG)$ which contain a snapshot the entropy, the velocity field and the magnetic fields:

- n_graph_step (default n_graph_step=0) is an integer. This is the number of timesteps between two graphic files
- n graphs (default n graphs=1) is an integer. This is the number of graphic files to be written.
- t_graph (default t_graph=-1.0 -1.0 ...) is real array, which contains the times when graphic files are requested.
- **dt_graph** (default dt_graph=0.0) is a real, which defines the time interval between graphic files.
- t_graph_start (default t_graph_start=0.0) is a real, which defines the time to start writing graphic files.

• t_graph_stop (default t_graph_stop=0.0) is a real, which defines the time to stop writing graphic files.

6.6.4 Spectra

The **spec** outputs controls the output of spectra: kinetic energy spectra (*kin_spec_#.TAG*), magnetic energy spectra (*mag_spec_#.TAG*) and thermal spectra (*T_spec_#.TAG*):

- n_spec_step (default n_spec_step=0) is an integer. This is the number of timesteps between two spectra.
- n_specs (default n_specs=0) is an integer. This is the number of spectra to be written.
- t_spec (default t_spec=-1.0 -1.0 ...) is real array, which contains the times when spectra are requested.
- dt_spec (default $dt_spec=0.0$) is a real, which defines the time interval between spectra.
- t_spec_start (default t_spec_start=0.0) is a real, which defines the time to start writing spectra.
- t_spec_stop (default t_spec_stop=0.0) is a real, which defines the time to stop writing spectra.
- l_2D_spectra (default l_2D_spectra.false.) is a logical. When set to .true., this logical enables the calculation of 2-D spectra in the (r,ℓ) and in the (r,m) parameter spaces. Those data are stored in the files named $2D_[mag|kin]_spec_\#.TAG$.

6.6.5 Movie files

The **movie** outputs controls the output of movie files (* *mov.TAG*).

Specific inputs

- l_movie (default l_movie=.false.) is a logical. It needs to be turned on to get movie computed.
 - Several movie-files can be produced during a run (it is now limited to 30 by the variable "n_movies_max" in the module movie). The movies are defined by a keyword determining the fields to be plotted and an expression that determines the nature of movie (r-slice, θ -slice, ϕ -slice, etc.). The code searches this information in a character string provided for each movie. These strings are elements of the array movie:
- movie (default movie=' ', ' ', ...) is a character string array. It contains the description of the movies one wants to compute.

For example, to invoke a movie(file) that shows (stores) the radial magnetic component of the magnetic field at the CMB, you have to provide the line

```
movie(1)="Br CMB",
```

in the &output namelist. Here, Br is the keyword for the radial component of the magnetic field and CMB is the expression that defines the movie surface. If, in addition, a movie of the temperature field at the meridional slice phi=0 and a movie of the z-vorticity in the equatorial plane are desired, the following line have to be added:

```
movie(2)="Temp phi=0",
movie(3)="Vortz eq",
```

Note that the code does **not interpret spaces and ignores additional characters** that do not form a keyword or a surface definition. Thus, for example Br or Bradial are all interpreted as the same keyword. Furthermore, the interpretation is **not case-sensitive**. The following table gives the possible keywords for movie calculations and their corresponding physical meaning:

Keyword	Fields stored in movie file
Br[radial]	Radial component of the magnetic field B_r .
Bt[heta]	Latitudinal component of the magnetic field B_{θ} .
Bp[hi]	Azimuthal component of the magnetic field B_{ϕ} .
Bh[orizontal]	The two horizontal components of the magnetic field.
Bs	Cylindrically radial component of the magnetic field B_s .
Ba[11]	All magnetic field components.
Fieldline[s] or FL	Axisymmetric poloidal field lines in a meridional cut.
AX[ISYMMETRIC]	Axisymmetric phi component of the magnetic field for $\phi = cst$.
B or AB	
Vr[adial]	Radial component of the velocity field u_r .
Vt[heta]	Latitudinal component of the velocity field u_{θ} .
Vp[hi]	Azimuthal component of the velocity field u_{ϕ} .
Vh[orizontal]	Horizontal velocity field, two components depending on the surface.
Va[ll]	All velocity field components.
Streamline[s] or SL	Field lines of axisymmetric poloidal field for $\phi = cst$.
AX[ISYMMETRIC]	Axisymmetric component of the velocity field for $\phi = cst$.
V or AV	
Vz	Vertical component of the velocity at the equator + vertical component
	of the vorticity at the equator (closest point to equator).
Voz	Vertical component of the vorticity ω_z .
Vor	Radial component of the vorticity ω_r .
Vop	Azimuthal component of vorticity ω_{ϕ}
Tem[perature] or En-	Temperature/Entropy
tropy	
Entropy (or	Axisymmetric temperature/entropy field for $\phi = cst$.
Tem[perature])	
AX[ISYMMETRIC]	
or AT	
Heat t[ransport]	Radial advection of temperature $u_r \frac{\partial s}{\partial r}$
HEATF	Conducting heat flux $\partial s/\partial r$
AX[iSYMMETRIC]	·
FL Pro	Axisymmetric field line stretching.
FL Adv	Axisymmetric field line advection.
FL Dif	Axisymmetric field line diffusion.
AB Pro	Toroidal axisymmetric field production.
AB Dif	Toroidal axisymmetric field diffusion.
Br Pro	Production of radial magnetic field B_r .
Br Adv	Advection of radial magnetic field B_r .
Br Dif	Diffusion of radial magnetic field B_r .
Jr	Radial component of the current j_r .
Jr Pro	Production of radial current + Ω -effect.
Jr Adv	Advection of the radial component of the current j_r .
Jr Dif	Diffusion of the radial component of the current j_r .
Bz Pol	Poloidal part of vertical component of the magnetic field B_z .
Bz Pol Pro	Production of the poloidal part of the vertical component of the mag-
	netic field B_z .
Bz Pol Adv	Advection of the poloidal part of the vertical component of the magnetic
	field B_z .
Bz Pol Dif	Diffusion of the poloidal part of the vertical component of the magnetic
	field B_z .
Jz Tor	Toroidal part of the vertical component of the current (j_z) .
l .	

Continued on next page

Table 6.1 – continued from previous page

Keyword	Fields stored in movie file
Jz Tor Pro	Production of the toroidal part of the vertical component of the current
	$ j_z.$
Jz Tor Adv	Advection of the toroidal part of the vertical component of the current
	$j_z.$
Jz Tor Dif	Diffusion of the toroidal part of the vertical component of the current
	$j_z.$
Bp Tor	Toroidal part of the azimuthal component of the magnetic field B_{ϕ} .
Bp Tor Pro	Production of the toroidal part of the azimuthal component of the mag-
	netic field B_{ϕ} .
Bp Tor Adv	Advection of the toroidal part of the azimuthal component of the mag-
	netic field B_{ϕ} .
Bp Tor Dif	Diffusion of the toroidal part of the azimuthal component of the mag-
	netic field B_{ϕ} .
HEL[ICITY]	Kinetic helicity $\mathcal{H} = oldsymbol{u} \cdot (oldsymbol{ abla} imes oldsymbol{u})$
AX[ISYMMETRIC	Axisymmetric component of the kinetic helicity.
HELICITY] or	
AHEL	
Bt Tor	Toroidal component of the latitudinal component of the magnetic field
	B_{θ} .
Pot Tor	Toroidal potential.
Pol Fieldlines	Poloidal fieldlines.
Br Shear	Azimuthal shear of the radial component of the magnetic field B_r
Lorentz[force] or LF	Lorentz force (only ϕ -component).
Br Inv	Inverse field apperance at CMB.

The following table gives the possible surface expression for movie calculations and their corresponding physical meaning:

Surface expression	Definition
CMB	Core-mantle boundary
Surface	Earth surface
EQ[uatot]	Equatorial plane
r=radius	Radial cut at r=radius with radius given in units of the outer core radius.
theta=colat	Latitudinal cut at theta=colat given in degrees
phi=phiSlice	Azimuthal cut ath phi=phiSlice given in degrees.
AX[isymmetric]	Axisymmetric quantity in an azimuthal plane
3D	3D array

Here is an additional example of the possible combinations to build your desired movie files.

```
l_movie = .true.,
movie(1) = "Br CMB",
movie(2) = "Vr EQ",
movie(3) = "Vortr r=0.8",
movie(4) = "Bp theta=45",
movie(5) = "Vp phi=10",
movie(6) = "entropy AX",
movie(7) = "vr 3D",
```

Standard inputs

- n_movie_step (default n_movie_step=0) is an integer. This is the number of timesteps between two movie outputs.
- n_movies (default n_movies=1) is an integer. This is the number of movie outputs to be written.
- t_movie (default t_movie=-1.0 -1.0 ...) is real array, which contains the times when movie outputs are requested.
- **dt_movie** (default dt_movie=0.0) is a real, which defines the time interval between movie outputs.
- t_movie_start (default t_movie_start=0.0) is a real, which defines the time to start writing movie outputs.
- t_movie_stop (default t_movie_stop=0.0) is a real, which defines the time to stop writing movie outputs.

6.6.6 Field Averages

The code can perform on-the-fly time-averaging of entropy, velocity field and magnetic field. Respective graphic output and spectra are written into the corresponding files (with *G_ave.TAG*, *kin_spec_ave.TAG*, *mag_spec_ave.TAG*). The time-averaged energies are written into the *log.TAG* file.

• l_average (default l_average=.false.) is a logical, which enables the time-averaging of fields when set to .true..

Warning: Time-averaging has a large memory imprint as it requires the storage of 3-D arrays. Be careful, when using large truncations.

6.6.7 Poloidal magnetic field potential at CMB

The **cmb** outputs controls the output of poloidal field potential coefficients at the CMB $b_{\ell m}(r=r_o)$: $B_coeff_cmb.TAG$ up to a maximum spherical harmonic degree 1 max cmb.

Note: This calculation is only enabled when <code>l_cmb_field=.true.or</code> when <code>l_dt_cmb_field=.true.</code>

Specific inputs

- l_cmb_field (default l_cmb_field=.false.) is a logical. It needs to be turned on to get cmb files computed.
- l_dt_cmb_field (default l_dt_cmb_field=.false.) is a logical. When set to .true., it allows the calculation of the secular variation of the magnetic field at the CMB.
- l_max_cmb (default l_max_cmb=14) is an integer. This is the maximum spherical harmonic degree ℓ stored in B_coeff_cmb.TAG, i.e. only $\ell \leq \ell_{maxcmb}$ are stored. For example, the following input parameter means that the B_coeff_cmb.TAG file is stored up to a spherical harmonic degree of ℓ :

```
l_cmb_field = .true.,
l_max_cmb = 20,
```

Standard inputs

- n_cmb_step (default $n_cmb_step=0$) is an integer. This is the number of timesteps between two cmb outputs.
- \mathbf{n} _cmbs (default n_cmbs=0) is an integer. This is the number of cmb outputs to be written.
- t_cmb (default t_cmb=-1.0 -1.0 ...) is real array, which contains the times when cmb outputs are requested.
- **dt_cmb** (default \(dt_cmb=0 \). (0) is a real, which defines the time interval between cmb outputs.
- t_cmb_start (default t_cmb_start=0.0) is a real, which defines the time to start writing cmb outputs.
- t_cmb_stop (default t_cmb_stop=0.0) is a real, which defines the time to stop writing cmb outputs.

6.6.8 Poloidal and toroidal potentials at several depths

The coeff_r# outputs controls the output of the poloidal and toroidal potential coefficients at several depths up to a maximum spherical harmonic degree l_{max_r} . The files B_{coeff_r} . The files B_{coeff_r} . The file B_{coeff_r} .

Note: This calculation is only enabled when l_r_field=.true. or when l_r_fieldT=.true..

Specific inputs

- l_r_field (default l_r_field=.false.) is a logical. It needs to be turned on to get r_field files computed.
- l_r_fieldT (default l_r_fieldT=.false.) is a logical. When set to .true., the thermal field is also stored in a file named T_coeff_r*.TAG.
- l_max_r (default $l_max_r=l_max$) is an integer. This is the maximum spherical harmonic degree ℓ stored in the r_field file, i.e. only $\ell \leq \ell_{maxcmb}$ are stored.

There are two ways to specify the radial grid points where you want to store the [B|V|T]_coeff_r#.TAG files. You can specify a stepping n_r_step: in that case 5 coeff_r#.TAG files will be stored at 5 different radial levels every n r step grid point:

```
l_r_field = .true.,
n_r_step = 6,
l_max_r = 30,
```

This will produces 5 files that contain the poloidal and toroidal potentials up to spherical harmonic degree $\ell = 30$:

- [B|V|T]_coeff_r1.TAG corresponds to the radial grid point with the index nR=6.
- [B|V|T]_coeff_r2.TAG to nR=12.
- [B|V|T]_coeff_r3.TAG to nR=18.
- [B|V|T]_coeff_r4.TAG to nR=24.
- [B|V|T]_coeff_r5.TAG to nR=30.
- n_r _step (default n_r _step=2) is an integer. This specifies the stepping between two consecutive [B|V|T]_coeff_r#.TAG files.

Alternatively, the input array n_r_array can be used to specify the radial grid points you exactly want to store:

```
l_r_field = .true.,
n_r_array = 8, 24, 47,
l_max_r = 10,
```

This will produces 3 files that contain the poloidal and toroidal potentials up to spherical harmonic degree $\ell = 10$:

- [B|V|T]_coeff_r1.TAG corresponds to the radial grid point with the index nR=8.
- [B|V|T]_coeff_r2.TAG to nR=24.
- [B|V|T]_coeff_r3.TAG to nR=47.
- n_r_array (default n_r_array=0 0 0 ...) a an integer array. You can specify the radial grid points (starting from n_r_cmb=1) where you want to store the coefficients.

Standard inputs

- n_r_field_step (default n_r_field_step=0) is an integer. This is the number of timesteps between two r_field outputs.
- n_r_fields (default n_r_fields=0) is an integer. This is the number of r_field outputs to be written.
- t_r_field (default t_r_field=-1.0 -1.0 ...) is real array, which contains the times when r_field outputs are requested.
- dt_r field (default dt_r field=0.0) is a real, which defines the time interval between r_f ield outputs.
- t_r_field_start (default t_r_field_start=0.0) is a real, which defines the time to start writing r_field outputs.
- t_r_field_stop (default t_r_field_stop=0.0) is a real, which defines the time to stop writing r_field outputs.

6.6.9 Poloidal and toroidal potentials in spectral and radial space

The [VIBIT]_Imr outputs controls the output of potential files ($V_{mr}\#.TAG$, $B_{mr}\#.TAG$ and $T_{mr}\#.TAG$). These are files contain the poloidal and toroidal flow and magnetic field potentials (and entropy/temperature) written in spectral and radial spaces (for instance w ($\lim_{m \to \infty}$, $\lim_{m \to \infty}$). These files can be pretty useful since they can be possibly used to reconstruct any quantity in the spectral space or in the physical space you may be interested in.

Specific inputs

They are two ways to store those files. The first option is to use <code>l_storePot=.true</code>. and the corresponding time control parameters (<code>n_pot_step</code>, <code>t_pot</code>, <code>n_pots</code>, etc.). In that case the three files <code>V_lmr_#.TAG</code>, <code>B_lmr_#.TAG</code> and <code>Tpot_#.TAG</code> will be stored. The following example will create new <code>V_lmr_#.TAG</code>, <code>Bpot_#.TAG</code> and <code>T_lmr_#.TAG</code> files every 1000 time steps:

```
1_storePot = .true.,
n_pot_step = 1000,
```

• l_storePot (default 1_storePot=.false.) is a logical. It needs to be turned on to store all the potentials in three different files: V_lmr_#.TAG, B_lmr_#.TAG and T_lmr_#.TAG.

The second option is control separately the writing of the three files using the three logicals <code>l_storeVpot</code>, <code>l_storeBpot</code> and <code>l_storeTpot</code> and their corresponding time control parameters. The following example

wrill create a new V_{lmr} #.TAG file every 1000 time steps and a new B_{lmr} #.TAG file every 3000 time steps (no T_{lmr} #.TAG files are stored in that case):

```
l_storeVpot = .true.,
n_Vpot_step = 1000,
l_storeBpot = .true.,
n_Bpot_step = 3000,
l_storeTpot = .false.,
```

- l_storeVpot (default l_storeVpot=.false.) is a logical. It needs to be turned on to store the flow poloidal and toroidal potentials. It then writes the V_lmr_#.TAG file.
- **l_storeBpot** (default *l_storeBpot=.false.*) is a logical. It needs to be turned on to store the magnetic field poloidal and toroidal potentials. It then writes the *B_lmr_#.TAG* file.
- **l_storeTpot** (default *l_storeTpot=.false.*) is a logical. It needs to be turned on to store the entropy. It then writes the *T lmr #.TAG* file.

Standard inputs

- n_pot_step (default $n_pot_step=0$) is an integer. This is the number of timesteps between two $[V|B|P]_lmr$ outputs.
- **n_pots** (default $n_pots=1$) is an integer. This is the number of $[V|B|P]_{n}$ outputs to be written.
- t_pot (default $t_pot=-1.0 -1.0 ...$) is real array, which contains the times when [V|B|P]_lmr outputs are requested.
- **dt_pot** (default $dt_pot=0.0$) is a real, which defines the time interval between two [V|B|P]_lmr outputs.
- t_pot_start (default t_pot_start=0.0) is a real, which defines the time to start writing [V|B|P]_lmr outputs.
- **t_pot_stop** (default *t_pot_stop=0.0*) is a real, which defines the time to stop writing [V|B|P]_lmr outputs.
- **n_Vpot_step** (default *n_Vpot_step=0*) is an integer. This is the number of timesteps between two V_lmr outputs.
- n Vpots (default n Vpots=1) is an integer. This is the number of Vlmr outputs to be written.
- t_Vpot (default t_Vpot=-1.0 -1.0 ...) is real array, which contains the times when V_lmr outputs are requested.
- **dt_Vpot** (default \(dt__Vpot=0.0 \)) is a real, which defines the time interval between \(V_\text{lmr} \) outputs.
- t_Vpot_start (default t_Vpot_start=0.0) is a real, which defines the time to start writing V_lmr outputs.
- t_Vpot_stop (default t_Vpot_stop=0.0) is a real, which defines the time to stop writing V_lmr outputs.
- n_Bpot_step (default n_Bpot_step=0) is an integer. This is the number of timesteps between two B_lmr outputs.
- n_Bpots (default n_Bpots=1) is an integer. This is the number of B_lmr outputs to be written.
- t_Bpot (default t_Bpot=-1.0 -1.0 ...) is real array, which contains the times when B_lmr outputs are requested.
- **dt_Bpot** (default dt_Bpot=0.0) is a real, which defines the time interval between B_1mr outputs.
- t_Bpot_start (default t_Bpot_start=0.0) is a real, which defines the time to start writing B_lmr outputs.
- t_Bpot_stop (default t_Bpot_stop=0.0) is a real, which defines the time to stop writing B_lmr outputs.

- n_Tpot_step (default n_Tpot_step=0) is an integer. This is the number of timesteps between two T_lmr outputs.
- n_Tpots (default n_Tpots=1) is an integer. This is the number of T_lmr outputs to be written.
- t_Tpot (default t_Tpot=-1.0 -1.0 ...) is real array, which contains the times when T_lmr outputs are requested.
- **dt_Tpot** (default \(dt_Tpot = 0 \). (0) is a real, which defines the time interval between T_lmr outputs.
- t_Tpot_start (default t_Tpot_start=0.0) is a real, which defines the time to start writing T_lmr outputs.
- t_Tpot_stop (default t_Tpot_stop=0.0) is a real, which defines the time to stop writing T_lmr outputs.

6.6.10 Torsional oscillations (TO)

Specific inputs

- **l_TO** (default *l_TO=.false.*) is a logical. It needs to be turned on to compute the torsional oscillations diagnostics (TO) computed.
- **1_TOmovie** (default 1_TOmovie=.false) is a logical. It needs to be turned on to store the *TO_movie.TAG* files.
- sDens (default sDens=1.0) is a float. It gives the relative point density of the cylindrical grid (in the radial direction).
- **zDens** (default *zDens=1*.0) is a float. It gives the relative point density of the cylindrical grid (in the vertical direction).

Standard inputs

- n_TO_step (default $n_TO_step=0$) is an integer. This is the number of timesteps between two TO outputs.
- **n_TOs** (default *n_TOs=1*) is an integer. This is the number of TO outputs to be written.
- t_TO (default t_TO=-1.0 -1.0 ...) is real array, which contains the times when TO outputs are requested.
- **dt_TO** (default $dt_TO=0$. 0) is a real, which defines the time interval between TO outputs.
- t_TO_start (default $t_TO_start = 0.0$) is a real, which defines the time to start writing TO outputs.
- t TO stop (default t TO stop=0.0) is a real, which defines the time to stop writing TO outputs.
- n TOZ step (default n TOZ step=0) is an integer. This is the number of timesteps between two TO outputs.
- n TOZs (default n TOZs=1) is an integer. This is the number of TO outputs to be written.
- t_TOZ (default t_TOZ=-1.0 -1.0 ...) is real array, which contains the times when TO outputs are requested.
- **dt_TOZ** (default \(dt_TOZ=0.0 \)) is a real, which defines the time interval between TO outputs.
- t_TOZ_start (default t_TOZ_start=0.0) is a real, which defines the time to start writing TO outputs.
- t_TOZ_stop (default t_TOZ_stop=0.0) is a real, which defines the time to stop writing TO outputs.
- n_TOmovie_step (default n_TOmovie_step=0) is an integer. This is the number of timesteps between two TO_mov outputs.
- n_TOmovie_frames (default n_TOmovies=1) is an integer. This is the number of TO_mov outputs to be written.

- t_TOmovie (default t_TOmovie=-1.0 -1.0 ...) is real array, which contains the times when TO_mov outputs are requested.
- **dt_TOmovie** (default dt_TOmovie=0.0) is a real, which defines the time interval between TO_mov outputs.
- t_TOmovie_start (default t_TOmovie_start=0.0) is a real, which defines the time to start writing TO_mov outputs.
- t_TOmovie_stop (default t_TOmovie_stop=0.0) is a real, which defines the time to stop writing TO_mov outputs.

6.6.11 RMS force balance

The code can compute the RMS contributions of the different forces that contribute to the Navier-Stokes equation and the the different terms that enter the induction equation.

- **l_RMS** (default *l_RMS=.false.*) is a logical, which enables the calculation of RMS force balance, when set to .true.. The outputs are stored in *dtVrms.TAG* and *dtBrms.TAG*.
- rCut (default rCut=0.0) is a float. This is the thickness of the layer which is left out at both boundaries for the RMS calculation. rCut=0.075 actually means that 7.5% below the CMB and above the ICB are disregarded in the force balance calculation.
- **rDea** (default *rDea=0.0*) is a float. This controls the dealiasing in RMS calculations. rDea=0.1 means that the highest 10% of the Chebyshev modes are set to zero.

6.6.12 Additional possible diagnostics

Geostrophy

- l_par (default l_par=.false.) is a logical. When set to .true., this logical enables additional calculations (for instance the degree of geostrophy). The details of these calculations can be found in the subroutine getEgeos in the Egeos.f90 file. These quantities are then stored in the columns 10-16 of the geos.TAG file.
- l_corrMov (default l_corrMov=.false.) is a logical. When set to .true., this logical enables the calculation of a movie file that stores North/South correlation in the CVorz_mov.TAG file.

Helicity

• l_hel (default l_hel=.false.) is a logical. When set to .true., this logical enables the calculation of helicity (RMS, northern and southern hemisphere, etc.). The outputs are stored in the columns 6-9 of the helicity.TAG file.

Power budget

• **l_power** (default *l_power.false.*) is a logical. When set to .true., this logical enables the calculation of input and output power (buoyancy, viscous and ohmic dissipations, torques). The time series are stored in *power.TAG* and *dtE.TAG* and the time-averaged radial profiles in *powerR.TAG*.

Angular momentum

• l_AM (default l_AM=.false.) is a logical. When set to .true., this logical enables the calculation of angular momentum. The time series are stored in AM.TAG.

Earth-likeness of the CMB field

- l_earth_likeness (default l_earth_likeness=.false.) is a logical. When set to .true., this logical enables the calculation of the Earth-likeness of the CMB magnetic field following (Christensen et al., 2010). The time series of the four criteria are stored in earth_like.TAG.
- l_max_comp (default l_max_comp=8) is an integer. This is the maximum spherical harmonic degree used to calculate the Earth-likeness of the CMB field.

Drift rates

• l_drift (default l_drift=.false.) is a logical. When set to .true., this logical enables the storage of some selected coefficients to allow the calculation of the drift rate. The time series are stored in drift[V|B][DQ].TAG.

Inertial modes

• l_iner (default l_iner=.false.) is a logical. When set to .true., this logical enables the storage of some selected $w(\ell, m)$ at mid-shell (stored in *inerP.TAG*) and $z(\ell, m)$ at mid-shell (stored in *inerT.TAG*). Those files can be further used to identify inertial modes.

Radial spectra

- l_rMagSpec (default l_rMagSpec=. false) is a logical. When set to .true., the magnetic spectra for the first 6 spherical harmonic degree ℓ for all radii are stored at times of log ouputs. This produces the unformatted fortran files rBrSpec.TAG and rBpSpec.TAG.
- I_DTrMagSpec (default 1_DTrMagSpec=.false) is a logical. When set to .true., the magnetic spectra of the magnetic field production terms for the first 6 spherical harmonic degree ℓ for all radii are stored at times of log ouputs. This produces the unformatted fortran files rBrProSpec.TAG, rBrAdvSpec.TAG, rBrDifSpec.TAG, rBpProSpec.TAG, rBpAdvSpec.TAG, rBpDifSpec.TAG and rBpDynSpec.TAG. All those files have exactly the same format as the rBrSpec.TAG.

Heat transport

• **l_fluxProfs** (default *l_fluxProfs=.false.*) is a logical. When set to .true., this logical enables the calculation of time-averaged radial heat flux profiles (conductive flux, convective flux, kinetic flux, viscous flux, Poynting flux and resistive flux). The time-averaged radial profiles are stored in the *fluxesR.TAG* file.

Boundary layer analysis

• l_viscBcCalc (default l_viscBcCalc=.false.) is a logical. When set to .true., this logical enables the calculation of time-averaged radial profiles that can be further use to determine the viscous and thermal boundary layer thicknesses: temperature, temperature variance, horizontal velocity, etc. The time-averaged radial profiles are stored in the bLayersR.TAG file.

Parallel/perpendicular decomposition

• l_perpPar (default l_perpPar=.false.) is a logical. When set to .true., this logical enables the decomposition of kinetic energy into components parallel and perpendicular to the rotation axis. The time series are stored in perpPar.TAG and the time-averaged radial profiles in perpParR.TAG.

Potential vorticity

• l_PV (default 1_PV=.false.) is a logical. When set to .true., this logical enables some potential vorticity diagnostics. At the end of the run, the results are stored in the the files PVZ.TAG and Vcy.TAG.

Pressure

• **l_PressGraph** (default *l_PressGraph=.true.*) is a logical. When set to .true., this logical enables the storage of pressure in the *graphic files*.

Time evolution of the m-spectra

- l_energy_modes (default l_energy_modes=.false.) is a logical. When set to .true., this logical enables the storage of the time-evolution of the kinetic and magnetic energy spectra for a given range of spherical harmonic orders: *time spectra*.
- m_max_modes (default m_max_modes=13) is an integer. This controls the maximum spherical harmonic order when l_energy_modes=.true..

6.6.13 Generic options

- **l_save_out** (default *l_save_out=.false.*) is a logical. When set to .true., the diagnostic files will be safely opened and closed before and after any outputs. When set to .false., the diagnostic files will be opened before the first iteration timestep and close at the end of the run. This may cost some computing time, but guarantees that only minimal information is lost in case of a crash.
- IVerbose (default *lVerbose=.false.*) is a logical. When set to .true., the code displays a lot of debugging informations.

```
Warning: Never set lVerbose to .true. for a production run!
```

• runid (default, runid="MAGIC default run") is a character string. This can be used to briefly describe your run. This information is then for instance stored in the header of the graphic files.

6.7 Mantle and Inner Core Namelists

6.7.1 Mantle Namelist

This namelist defines mantle properties

- conductance_ma (default conductance_ma=0.0) is a real that defines the conductance (dimensionless) of the mantle.
- **nRotMa** (default nRotMa=0) is an integer that defines the rotation of the mantle:

nRotMa=-1	Mantle rotates with prescribed rate (see omega_ma1 and omega_ma2 below)
nRotMa=0	Fixed, non-rotating mantle
nRotMa=1	Mantle rotates according to torques

- **rho_ratio_ma** (default *rho_ratio_ma=1*) is a real which gives the density of the mantle in terms of that of the outer core.
- omega_ma1 (default omega_ma1=0.0) is a real which defines a mantle rotation rate (used when nRotMa=-1).
- omegaOsz_ma1 (default omegaOsz_ma1=0.0) is a real which prescribes the oscillation frequency of the mantle rotation rate. In this case, omega_ma1 is the amplitude of the oscillation.
- **tShift_ma1** (default *tShift_ma1=0.0*) is a real which defines the time shift of the mantle rotation rate omega_ma1.
- omega_ma2 (default omega_ma2=0.0) is a real which defines a second mantle rotation rate.
- omegaOsz_ma2 (default omegaOsz_ma2=0.0) is a real which defines the oscillation frequency of the second mantle rotation rate omega_ma2.
- tShift_ma2 (default tShift_ma2=0.0) is a real which defines the time shift for omega_ma2.

The resultant prescribed mantle rotation rate is computed as:

```
omega_ma = omega_ma1*cos(omegaOsz_ma1*(time+tShift_ma1)) + &
    omega_ma2*cos(omegaOsz_ma2*(time+tShift_ma2))
```

The following defines the parameters when one wants to excite inertial modes in the system artificially using a method similar to Rieutord et. al 2012.

- amp_RiMaSym (default amp_RiMaSym=0.0) is a real which defines the amplitude of forcing on the outer boundary for an equatorially symmetric mode
- omega_RiMaSym (default omega_RiMaSym=0.0) is a real which defines the frequency of forcing on the outer boundary for an equatorially symmetric mode
- m_RiMaSym (default m_RiMaSym=0.0) is an integer which defines the wavenumber of the equatorially symmetric mode one wants to excite

The following variables define the same for an equatorially anti-symmetric mode:

- amp_RiMaAsym (default amp_RiMaAsym=0.0)
- omega_RiMaAsym (default omega_RiMaAsym=0.0)
- m_RiMaAsym (default m_RiMaAsym=0.0)

6.7.2 Inner Core Namelist

This namelist defines properties of the inner core

- **sigma_ratio** (default *sigma_ratio=0.0*) is a real that defines the conductivity of the inner core with respect to the value of the outer core. sigma_ratio=0 thus corresponds to a non-conducting inner core.
- **nRotIc** (default *nRotIc=0*) is an integer that defines the rotation of the inner core. Behaves the same way as *nRotMa* (above).
- **rho_ratio_ic** (default *rho_ratio_ic=1.0*) is a real which defines the density of the inner core in terms of that of the outer core.
- **BIC** (default BIC=0.0) is a real which gives the imposed dipole field strength at the Inner Core Boundary. Having BIC > 0 implies that the inner core acts as a dipole magnet as implemented in the DTS experiment at Grenoble, France.

• Variables prescribing rotation rate of inner core The following variables are used to prescribe rotation rate of the inner core. They behave in the same way as the corresponding variables for the mantle. They are used only when nRotIC=0.

```
omega_ic1 (default omega_ic1=0.0)
omegaOsz_ic1 (default omegaOsz_ic1=0.0)
tShift_ic1 (default tShift_ic1=0.0)
omega_ic2 (default omega_ic2=0.0)
omegaOsz_ic2 (default omegaOsz_ic2=0.0)
tShift_ic2 (default tShift_ic2=0.0)
```

As with the mantle, the resultant prescribed rotation rate for the inner core is computed as:

```
omega_ic = omega_ic1*cos(omegaOsz_ic1*(time+tShift_ic1)) + &
    omega_ic2*cos(omegaOsz_ic2*(time+tShift_ic2))
```

The following, as for the mantle namelist, is for artificially exciting inertial modes in the spherical shell, but for the inner boundary.

- amp_RiIcSym (default amp_RiIcSym=0.0) is a real which defines the amplitude of forcing on the inner boundary for an equatorially symmetric mode
- omega_RiIcSym (default omega_RiIcSym=0.0) is a real which defines the frequency of forcing on the inner boundary for an equatorially symmetric mode
- m_RiIcSym (default m_RiIcSym=0.0) is an integer which defines the wavenumber of the equatorially symmetric mode one wants to excite

The following variables define the same for an equatorially anti-symmetric mode:

- amp_RiIcAsym (default amp_RiIcAsym=0.0)
- omega_RiIcAsym (default omega_RiIcAsym=0.0)
- m_RiIcAsym (default m_RiIcAsym=0.0)

INTERACTIVE COMMUNICATION WITH THE CODE USING SIGNAL. TAG

It is possible to interactively communicate with the MagIC code **during a run**, using a file which is systematically created when the simulation starts, called **signal.TAG**. By default, this file contains only the word NOT and does nothing to the simulation. Replacing NOT by one of the following allowed keywords will have some influence on the outputs or possibly force the code to terminate its execution:

- **END**: Changing the word NOT to END will cause the code to finish after the current time step and write all the outputs as if it was programmed to finish at that time from the start. This will thus normally produce the *checkpoint_end.TAG* file that will possibly allow you to continue this run later at your convenience.
- **GRA**: Changing the word NOT to GRA will cause the code to produce a graphic ouptut file *G_#.TAG*. The keyword will be automatically restored to NOT once the graphic file has been produced.
- **RST**: Changing the word NOT to RST will cause the code to produce a restart file *check-point_t#.TAG*. The keyword will then be restored to NOT once the restart file has been written.
- **SPE**: Changing the word NOT to SPE will cause the code to produce spectra *kin_spec_#.TAG* (and possibly *mag_spec_#.TAG* and *T_spec_#.TAG* <*secTSpecFile>* depending if the run is magnetic or not, or if it solves a temperature/entropy equation). Once the spectra files have been written, the keyword will be automatically replaced by NOT.
- **POT**: Changing the word NOT to POT will cause the code to produce the potential files *V_lmr_#.TAG* (and possibly *B_lmr_#.TAG* and *T_lmr_#.TAG* < *secTpotFile>* depending if the run is magnetic or not, or if it solves a temperature/entropy equation). Once the potential files have been written, the keyword will be automatically replaced by NOT.

Note: Those keywords are **case-insensitive**.

Instead of editing the file with your favorite editor to specify the requested keyword, we recommand using instead the shell command echo to avoid some possible crash during the code execution when writing into the signal.TAG file. For instance, if you want a *graphic output file*, just use the following command (adapted to your current *TAG*):

\$ echo GRA > signal.TAG

OUTPUT FILES

While some information of a run is written into STDOUT to monitor its progress, most outputs are printed into dedicated files identified by the chosen *TAG* extension. These files can be parsed and analysed using the *python classes*. The following pages describe the content and the structure of the different type of output files:

- 1. Most of the information found in STDOUT is also written to the **log-file** called *log.TAG*. In addition, this file contains all input parameters, truncation, information on other output files, and some results like the time averaged energies (when *l_average=.true*.).
- 2. There are several ascii files that contain the **time-evolution of integrated quantities** (energies, heat fluxes, rotation rate, Reynolds numbers, etc.) that are systematically produced:
 - Kinetic energies: *e_kin.TAG*,
 - Magnetic energies: *e_mag_oc.TAG* and *e_mag_ic.TAG*,
 - Rotation rates: rot. TAG,
 - Informations about the dipolar component of the magnetic field: dipole.TAG,
 - Diagnostic parameters (Reynolds, Elsasser, etc.): par.TAG,
- 3. There are **additional conditional time series** that contain the time-evolution of other physical quantities that depend on the chosen *input parameters*:
 - Angular momentum balance: AM.TAG,
 - Heat transport: heat.TAG,
 - Helicity: *helicity.TAG*,
 - Power budget: power.TAG and dtE.TAG,
 - Square velocities: u_square.TAG,
 - Drift rates: drift[V\B][D\Q].TAG and iner[P\T].TAG,
 - Torques: SR[IC|MA].TAG,
 - Geostrophy: geos. TAG,
 - RMS calculations of the force balances: dtVrms.TAG and dtBrms.TAG,
 - Kinetic energies perpendicular and parallel to the rotation axis: *perpPar.TAG*.
- 4. Time-averaged radial profiles:
 - Kinetic energies: eKinR.TAG,
 - Magnetic energies: eMagR.TAG,
 - Diagnostic quantities: parR.TAG,

- Power budget: powerR.TAG,
- Average temperature, entropy and pressure: heatR.TAG,
- Heat fluxes: fluxesR.TAG,
- Temperature and horizontal velocities: bLayersR.TAG,
- Kinetic energies perpendicular and parallel to the rotation axis: *perpParR.TAG*.
- 5. **Radial profiles of the transport properties** of the reference state (those files will only be produced when the appropriate input option is chosen):
 - Temperature, density and gravity: anel.TAG,
 - Electrical conductivity: varCond.TAG,
 - Thermal conductivity: *varDiff.TAG*,
 - Kinematic viscosity: varVisc.TAG,
 - Mapping of the Chebyshev grid: *rNM.TAG*.
- 6. Kinetic energy, magnetic energy and temperature/entropy spectra:
 - Kinetic energy: kin_spec_#.TAG,
 - Magnetic energy: kin_spec_#.TAG,
 - Velocity square: u2_spec_#.TAG,
 - Temperature/entropy: *T_spec_#.TAG*,
 - Time-averaged kinetic energy: kin_spec_ave.TAG,
 - Time-averaged magnetic energy: mag_spec_ave.TAG,
 - Time-averaged temperature/entropy: *T_spec_ave.TAG*,
 - 2-D ([r,ell] and [r,m]) spectra: 2D_[mag|kin]_spec_#.TAG.
 - Time-averaged 2-D ([r,ell] and [r,m]) spectra: $2D_{mag|kin}_{spec}_{ave.TAG}$.
- 7. Output snapshot that contains the 3-D components of the velocity field, the magnetic field and the temperature/entropy. Those files are named **graphic files** *G_#.TAG* (or *G_ave.TAG* for its time-averaged counterpart).
- 8. Time evolution of some chosen fields. Those files are named **movie files**: *_mov.TAG.
- 9. Checkpoints outputs that will allow the code to restart. Those files are named **restart files**: *checkpoint_end.TAG*.
- 10. **Time-evolution of the poloidal and toroidal coefficients** at diffent depths:
 - Time evolution of the poloidal magnetic field at the CMB: B coeff cmb.TAG,
 - Time evolution of the potentials at several depths: [V|T|B]_coeff_r#.TAG
- 11. Additional specific outputs:
 - Torsional oscillations (see *here*),
 - Potential files: V_lmr_#.TAG, B_lmr_#.TAG and T_lmr_#.TAG,
 - Potential vorticity files: PVZ.TAG and Vcy.TAG,
 - Magnetic spectra for various radii: rB[r|p]Spec.TAG.

8.1 Log file: log. TAG

This is a text file contains information about the run, including many of the things which are printed to STDOUT. It has the following information in order of appearance:

- Code version: the version of the code
- Parallelization: information about number of MPI ranks being used, blocking information of OpenMP chunks and processor load balancing
- Namelists: displays values of all namelist variables. The ones input by the user should have the input values while the rest of them are set to their default values.
- Mode The mode of the run self-consistent/kinematic dynamo, convection, couette flow etc. See the control
 namelist for more information about mode.
- **Grid parameters**: information about the grid sizes and truncation being used. More information about this in the *grid namelist*. If a new grid, different from that in the restart file is used, then a comparison is shown between old and new grid parameters and the user is informed that the data is being mapped from the old to the new grid.
- **Progress**: information about the progress of the run for every 10% of the run and the mean wall time for time step.
- Writing of graphic, movie, restart and spectra files: displays the time step and tells the user whenever a *G_#.TAG*, *checkpoint_#.TAG* or *spectra* file or a *movie frame* is written disk.
- Energies: gives kinetic and magnetic energies (total, poloidal, toroidal, total density) at the end of the run.
- **Time averages**: this part gives time averaged kinetic and magnetic energies (total, poloidal, toroidal, total density) and time averaged parameters (Rm, Elsass, Rol etc.). If *l_average=.true*., this section also provides information about average spectra and graphic files being written.
- Wall times: this is the last part of the log file and it provides information about the mean wall time for running different parts of the code. These values can be used to judge the speed and scaling capabilities of your computer.

Most of these informations can be parsed and stored into a python class using MagicSetup:

```
>>> # read log.N0m2
>>> stp = MagicSetup(nml='log.N0m2')
>>> print(stp.ek, stp.prmag) # print Ekman and magnetic Prandtl numbers
>>> print(stp.l_max) # print l_max
```

8.2 Default time-series outputs

8.2.1 e kin. TAG

This file contains the kinetic energy of the outer core, defined by

$$E_{k} = \frac{1}{2} \int_{V} \tilde{\rho} u^{2} \, dV = E_{pol} + E_{tor}$$

$$= \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \frac{1}{\tilde{\rho}} \left[\frac{\ell(\ell+1)}{r^{2}} |W_{\ell m}|^{2} + \left| \frac{dW_{\ell m}}{dr} \right|^{2} \right] dr$$

$$+ \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \frac{1}{\tilde{\rho}} |Z_{\ell m}|^{2} dr$$
(8.1)

The detailed calculations are done in the subroutine get e kin. This file cont
--

No. of column	Contents
1	time
2	poloidal energy
3	toroidal energy
4	axisymmetric poloidal energy
5	axisymmetric toroidal energy
6	equatorial symmetric poloidal energy
7	equatorial symmetric toroidal energy
8	equatorial symmetric and axisymmetric poloidal energy
9	equatorial symmetric and axisymmetric toroidal energy

```
>>> # To stack all the e_kin.TAG files of the current directory
>>> ts = MagicTs(field='e_kin', all=True)
>>> # To only read e_kin.NOm2
>>> ts = MagicTs(field='e_kin', tag='NOm2')
```

8.2.2 e_mag_oc.TAG

This file contains the magnetic energy of the outer core, defined by

$$E_{m} = \frac{1}{2} \int_{V} B^{2} \, dV = E_{pol} + E_{tor}$$

$$= \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \left[\frac{\ell(\ell+1)}{r^{2}} |b_{\ell m}|^{2} + \left| \frac{db_{\ell m}}{dr} \right|^{2} \right] dr$$

$$+ \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} |j_{\ell m}|^{2} dr$$
(8.2)

The detailed calculations are done in the subroutine get_e_mag . This file contains the following informations:

No. of column	Contents
1	time
2	outer core poloidal energy
3	outer core toroidal energy
4	outer core axisymmetric poloidal energy
5	outer core axisymmetric toroidal energy
6	outside potential field energy
7	outside axisymmetric potential field energy
8	equatorial symmetric poloidal energy
9	equatorial symmetric toroidal energy
10	equatorial symmetric and axisymmetric poloidal energy
11	equatorial symmetric and axisymmetric toroidal energy
12	outside potential field energy
13	outside potential field axisymmetric energy

This file can be read using MagicTs with the following options:

```
>>> # To stack all the e_mag_oc.TAG files of the current directory
>>> ts = MagicTs(field='e_mag_oc', all=True)
>>> # To only read e_mag_oc.N0m2
>>> ts = MagicTs(field='e_mag_oc', tag='N0m2')
```

8.2.3 e_mag_ic.TAG

This file contains the magnetic energy of the inner core. The detailed calculations are done in the subroutine get_e_mag . This file contains the following informations:

No. of column	Contents
1	time
2	inner core poloidal energy
3	inner core toroidal energy
4	inner core axisymmetric poloidal energy
5	inner core axisymmetric toroidal energy

This file can be read using MagicTs with the following options:

```
>>> # To stack all the e_mag_ic.TAG files of the current directory
>>> ts = MagicTs(field='e_mag_ic', all=True)
>>> # To only read e_mag_ic.N0m2
>>> ts = MagicTs(field='e_mag_ic', tag='N0m2')
```

8.2.4 rot. TAG

This files contains the rotation of the inner core and the mantle. Output concerning the rotation of inner core and mantle. This file is written by the subroutine write_rot.

No. of column	Contents
1	time
2	Inner core rotation rate
3	Lorentz torque on inner core
4	viscous torque on inner core
5	mantle rotation rate
6	Lorentz torque on mantle
7	viscous torque on mantle

This file can be read using MagicTs with the following options:

```
>>> # To stack all the rot.TAG files of the current directory
>>> ts = MagicTs(field='rot', iplot=False, all=True)
```

8.2.5 dipole.TAG

This file contains several informations about the magnetic dipole. This file is written by the subroutine get_e_mag .

No. of	Contents
column	
1	time
2	tilt angle (colatitude in degrees) of the dipole
3	longitude (in degress) of dipole-pole
4	relative energy of the axisymmetric dipole
5	relative energy of the axisymmetric dipole at the CMB
6	energy of the axisymmetric dipole at the CMB normalized with the total energy up to
	spherical harmonic degree and order 11
7	relative energy of the total (axisymmetric and equatorial) dipole
8	relative energy of the total (axisymmetric and equatorial) dipole in the outer core
9	relative energy of the total dipole (axisymmetric and equatorial) at the CMB
10	energy of the total (axisymmetric and equatorial) dipole at the CMB
11	energy of the axisymmetric dipole at the CMB
12	energy of the dipole
13	energy of the axisymmetric dipole
14	magnetic energy at the CMB
15	magnetic energy up to spherical harmonic degree and order 11
16	ratio between equatorial dipole energy and equatorial poloidal energy
17	difference between energy at the CMB and equatorial symmetric energy at the CMB,
	normalized by energy at the CMB
18	difference between energy at the CMB and axisymmetric energy at the CMB, normalized
	by energy at the CMB
19	difference between total energy and equatorial symmetric part of the total energy, nor-
	malized by the total energy
20	difference between total energy and axisymmetric part of the total energy, normalized
	by the total energy

```
>>> # To stack all the dipole.TAG files of the current directory
>>> ts = MagicTs(field='dipole', all=True)
```

8.2.6 par. TAG

This files contains the outputs of several parameters that describe flow and magnetic fields (Reynolds number, Elsasser number, flow lengthscales, etc.). This file is written by the subroutine output.

No. of column	Contents
1	time
2	(magnetic) Reynolds number
3	Elsasser number
4	Local Rossby number Rol
5	Realtive geostrophic kinetic energy
6	Total dipolarity
7	CMB dipolarity
8	Axial flow length scale dlV
9	Flow length scale dmV
10	Flow length scale dpV
11	Flow length scale dzV
12	Dissipation length scale lvDiss
13	Dissipation length scale lbDiss
14	Magnetic length scale dlB
15	Magnetic length scale dmB
16	Elsasser number at CMB
17	Local Rol based on non-ax. flow
18	Convective flow length scale dlVc
19	CMB zonal flow at the equator

```
>>> # To stack all the par.TAG files of the current directory
>>> ts = MagicTs(field='par', all=True)
```

8.3 Additional optional time-series outputs

8.3.1 heat.TAG

This files contains informations about the heat transfer (Nusselt number, entropy and temperature at both boundaries). This file is written by the subroutine <code>outHeat</code>.

No. of column	Contents
1	time
2	Nusselt number at the inner boundary
3	Nusselt number at the outer boundary
4	Nusselt number based on ΔT ratio
5	Temperature at the inner boundary
6	Temperature at the outer boundary
7	Entropy at the inner boundary
8	Entropy at the outer boundary
9	Heat flux at the inner boundary
10	Heat flux at the outer boundary
11	Pressure perturbation at the outer boundary
12	volume integrated mass perturbation
13	Sherwood number at the inner boundary
14	Sherwood number at the outer boundary
15	Sherwood number based on $\Delta \xi$ ratio
16	Chemical composition at the inner boundary
17	Chemical composition at the outer boundary

```
>>> # To stack all the heat.TAG files of the current directory
>>> ts = MagicTs(field='heat', all=True)
```

8.3.2 AM. TAG

Note: This file is **only** written when $l_AM = .true$.

This file contains the time series of the angular momentum of the inner core, the outer core and the mantle. This file is written by the subroutine $write_rot$.

No. of column	Contents
1	time
2	angular momentum of the outer core
3	angular momentum of the inner core
4	angular momentum of the mantle
5	total angular momentum
6	relative in angular momentum, per time step
7	total kinetic angular momentum
8	relative change in kinetic energy, per time step
9	kinetic angular momentum of the inner core
10	kinetic angular momentum of the outer core
11	kinetic angular momentum of the mantle

This file can be read using MagicTs with the following options:

```
>>> # To stack all the AM.TAG files of the current directory
>>> ts = MagicTs(field='AM', all=True)
```

8.3.3 power.TAG

Note: This file is **only** written when $l_power=.true$.

This file contains the power budget diagnostic. This file is computed by the subroutine get_power.

No. of column	Contents
1	time
2	Buoyancy power: $Ra g(r) \langle u_r T' \rangle_s$
3	Chemical power: $Ra_{\xi} g(r) \langle u_r \xi' \rangle_s$
4	Viscous power at the inner boundary (ICB)
5	Viscous power at the outer boundary (CMB)
6	Viscous dissipation: $\langle (\nabla \times u)^2 \rangle_s$
7	Ohmic dissipation: $\langle (\nabla \times B)^2 \rangle_s$
8	Total power at the CMB (viscous + Lorentz)
9	Total power at the ICB (viscous + Lorentz)
10	Total power
11	Time variation of total power

This file can be read using MagicTs with the following options:

```
>>> # To stack the files that match the pattern ``power.N0m2*``
>>> ts = MagicTs(field='power', tags='N0m2*')
```

8.3.4 dtE.TAG

Note: This file is **only** written when $l_power=.true$.

This file contains the time-derivatives of the total energy. It allows to accurately monitor how the total energy varies with time. This file is generated by the subroutine output.

No. of column	Contents
1	time
2	time-derivative of the total energy $\partial E/\partial t$
3	integrated time variation of the total energy
4	relative time variation of the total energy

8.3.5 earth_like.TAG

This contains informations about the Earth-likeness of the CMB radial magnetic field. This file is written by the subroutine get_e_mag .

Note: This file is **only** calculated when $l_{earth_like} = .true$..

No. of column	Contents
1	time
2	Ratio of axial dipole to non-dipole component at the CMB
3	Equatorial symmetry of the CMB field (odd/even ratio)
4	Zonality: zonal to non-zonal ratio of the CMB field
5	Magnetic flux concentration at the CMB

The details of the calculations are given in (Christensen et al., 2010).

This file can be read using MagicTs with the following options:

```
>>> # To stack all the earth_like.TAG files of the current directory
>>> ts = MagicTs(field='earth_like', all=True)
```

8.3.6 geos. TAG

This file contains informations about the geostrophy of the flow. This file is written by the subroutine getEgeos.

Note: This file is **only** calculated when $l_par=.true$..

No. of column	Contents
1	time
2	Relative geostrophic kinetic energy
3	Relative kinetic energy in the northern part of the TC
4	Relative kinetic energy in the southern part of the TC
5	Kinetic energy (calculated on the cylindrical grid)
6	North/South correlation of Vz, outside the TC
7	North/South correlation of vorticity outside the TC
8	North/South correlation of helicity outside the TC

This file can be read using MagicTs with the following options:

```
>>> # To stack all the geos.TAG files of the current directory
>>> ts = MagicTs(field='geos', all=True)
```

8.3.7 helicity.TAG

This files contains informations about the kinetic helicity in both the Northern and the Southern hemispheres. This file is written by the subroutine <code>outHelicity</code>.

Note: This file is **only** calculated when $l_hel=.true$..

No. of column	Contents
1	time
2	Helicity (northern hemisphere)
3	Helicity (southern hemisphere)
4	RMS helicity (northern hemisphere)
5	RMS helicity (southern hemisphere)
6	Helicity (northern hemisphere, only non-axisym. flow)
6	Helicity (southern hemisphere, only non-axisym. flow)
8	RMS helicity (northern hemisphere, only non-axisym. flow)
9	RMS helicity (southern hemisphere, only non-axisym. flow)

```
>>> # To stack all the helicity.TAG files of the current directory
>>> ts = MagicTs(field='helicity', all=True)
```

8.3.8 u_square.TAG

Note: This file is **only** written in an elastic models, i.e. either when *strat/=0* or when *interior_model/="None"*

This file contains the square velocity of the outer core. It is actually very similar to the $e_kin.TAG$ file, except that the density background $\tilde{\rho}$ is removed:

$$\mathcal{U} = \frac{1}{2} \int_{V} u^{2} \, dV = \mathcal{U}_{pol} + \mathcal{U}_{tor}$$

$$= \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \frac{1}{\tilde{\rho}^{2}} \left[\frac{\ell(\ell+1)}{r^{2}} |W_{\ell m}|^{2} + \left| \frac{dW_{\ell m}}{dr} \right|^{2} \right] dr$$

$$+ \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \frac{1}{\tilde{\rho}^{2}} |Z_{\ell m}|^{2} dr$$

The detailed calculations are done in the subroutine get_u_square. This file contains the following informations:

No. of columns	Contents
1	time
2	poloidal part \mathcal{U}_{pol}
3	toroidal part \mathcal{U}_{pol}
4	axisymmetric contribution to the poloidal part
5	axisymmetric contribution to the toroidal part
6	Rossby number: $Ro = E\sqrt{\frac{2\mathcal{U}}{V}}$
7	Magnetic Reynolds number: $Rm = Pm \sqrt{\frac{2\mathcal{U}}{V}}$
8	local Rossby number: $Ro_l = Ro\frac{d}{l}$
9	average flow length scale: l
10	local Rossby number based on the non-axisymmetric components of the flow
11	average flow length scale based on the non-axisymmetric components of the flow

This file can be read using MagicTs with the following options:

```
>>> # To stack all the u_square.TAG files of the current directory
>>> ts = MagicTs(field='u_square', all=True)
```

8.3.9 drift[V|B][D|Q].TAG

Note: These files are **only** written when $l_drift = .true$.

These files store spherical harmonic coefficients of the toroidal (poloidal) potential of the flow (magnetic) field, only for $\ell = m$ or $\ell = m+1$ depending on the symmetry - D for **D** ipolar and Q for **Q** uadrupolar. The coefficients are stored at different three different radial levels - n_r1, nr_2, n_r3 for the velocity and two different radial levels - n_r1 and n_r2 - for the magnetic field.

The symmetries can be summarized below:

Field	Dipolar	Quadrupolar
Velocity	$\ell = m$	$\ell = m + 1$
Magnetic	$\ell = m + 1$	$\ell = m$

 $\ell+m=$ even for toroidal potential refers to an equatorially antisymmetric field (Dipolar), while the same for a poloidal potential is associated with an equatorially symmetric field (Quadrupolar). The sense is opposite when $\ell+m=$ odd. This is the reason for the choice of selecting these specific coefficients.

The columns of the files look like follows:

For the flow field:

- $n_r1 = (1/3) * n_r_max-1$
- $n_r2 = (2/3) * n_r_max-1$
- $n_r3 = n_r_{max-1}$

Column no.	DriftVD.TAG	DriftVQ.TAG
1	Time	Time
2	z (minc, minc) at n_r1	$z (minc+1, minc)$ at n_r1
3	z (2*minc, 2*minc) at n_r1	z (2*minc+1, 2*minc) at n_r1
4	z (3*minc, 3*minc) at n_r1	z (3*minc+1, 3*minc) at n_r1
5	z (4*minc, 4*minc) at n_r1	z (4*minc+1, 4*minc) at n_r1
6	z (minc, minc) at n_r2	z (minc+1, minc) at n_r2
7	z (2*minc, 2*minc) at n_r2	z (2*minc+1, 2*minc) at n_r2
8	z (3*minc, 3*minc) at n_r2	z (3*minc+1, 3*minc) at n_r2
9	z (4*minc, 4*minc) at n_r2	z (4*minc+1, 4*minc) at n_r2
10	z (minc, minc) at n_r3	z (minc+1, minc) at n_r3
11	z (2*minc, 2*minc) at n_r3	z (2*minc+1, 2*minc) at n_r3
12	z (3*minc, 3*minc) at n_r3	z (3*minc+1, 3*minc) at n_r3
13	z (4*minc, 4*minc) at n_r3	z (4*minc+1, 4*minc) at n_r3

Chapter 8. Output files

For the magnetic field:

• $n_r1 = n_r ICB$

•
$$n_r^2 = n_r CMB$$

Column no.	DriftBD.TAG	DriftBQ.TAG
1	Time	Time
2	b (minc+1, minc) at n_r1	b (minc, minc) at n_r1
3	b (2*minc+1, 2*minc) at n_r1	b (2*minc, 2*minc) at n_r1
4	b (3*minc+1, 3*minc) at n_r1	b (3*minc, 3*minc) at n_r1
5	b (4*minc+1, 4*minc) at n_r1	b (4*minc, 4*minc) at n_r1
6	b (minc+1, minc) at n_r2	b (minc, minc) at n_r2
7	b (2*minc+1, 2*minc) at n_r2	b (2*minc, 2*minc) at n_r2
8	b (3*minc+1, 3*minc) at n_r2	b (3*minc, 3*minc) at n_r2
9	b (4*minc+1, 4*minc) at n_r2	b (4*minc, 4*minc) at n_r2

Analysis of these files can give you information about the drift frequency of the solution and it's symmetry.

8.3.10 iner[P|T].TAG

Note: These files are **only** written when $l_iner=.true$. and minc = 1.

These files contain time series of spherical harmonic coefficients upto degree, $\ell=6$ at a radius $r=(r_{cmb}-r_{icb})/2$. The inerp.TAG contains coefficients of the poloidal potential while the inerp.TAG contains coefficients of the toroidal potential. These files are written by the subroutine $write_rot$. The oscillations of these coefficients can be analysed to look for inertial modes. The columns of the inerp.TAG look like follows:

No. of column	Coefficient
1	$w(\ell=1, m=1)$
2	$w(\ell=2, m=1)$
3	$w(\ell=2, m=2)$
4	$w(\ell=3, m=1)$
20	$w(\ell = 6, m = 5)$
21	$w(\ell = 6, m = 6)$

where $w(\ell, m)$ is the poloidal potential with degree ℓ and order m.

The columns of the inerT.TAG follow the following structure:

No. of column	Coefficient
1	$z(\ell=1, m=1)$
2	$z(\ell=2, m=1)$
3	$z(\ell=2, m=2)$
4	$z(\ell=3, m=1)$
20	$z(\ell=6, m=5)$
21	$z(\ell=6, m=6)$

where $z(\ell, m)$ is the toroidal potential with degree ℓ and order m.

8.3.11 SR[IC|MA].TAG

Note: These files are **only** written for nRotIc=-1 (for SRIC.TAG) or nRotMa=-1 (for SRMA.TAG). In other words, these outputs are produced **only** when one of the boundaries is made to rotate at a prescribed rotation rate.

These files contain information about power due to torque from viscous and Lorentz forces at the inner core boundary (SRIC.TAG) or core mantle boundary (SRMA.TAG). The columns look like follows:

No. of column	Contents
1	Time
2	$\Omega_{IC} \Omega_{MA}$
3	Total power = Lorentz + Viscous
4	Viscous power
5	Lorentz force power

8.3.12 dtVrms.TAG

Note: This file is **only** written when $l_RMS=.true$.

This files contains the RMS force balance of the Navier Stokes equation. This file is written by the subroutine dt Vrms.

No. of column	Contents
1	time
2	Flow changes: inertia-advection
3	Coriolis force
4	Lorentz force
5	Advection term
6	Diffusion term
7	Buoyancy term
8	Pressure gradient term
9	Sum of force terms: geostrophic balance
10	Sum of force terms: pressure, Coriolis and Lorentz
11	Sum of force terms: pressure, buoyancy and Coriolis
12	Sum of force terms: pressure, buoyancy, Coriolis and Lorentz
13	Sum of force terms: Lorentz/Coriolis
14	Sum of force terms: Pressure/Lorentz
15	Sum of force terms: Coriolis/Inertia/Archimedean

This file can be read using MagicTs with the following options:

```
>>> # To stack all the dtVrms.TAG files of the current directory
>>> ts = MagicTs(field='dtVrms', all=True)
```

8.3.13 dtBrms.TAG

Note: This file is **only** written when $l_RMS=.true$.

This files contains the RMS terms that enter the induction equation. This	is file is written by the subroutine dtBrms.
---	--

No. of column	Contents
1	time
2	Changes in magnetic field (poloidal)
3	Changes in magnetic field (toroidal)
4	Poloidal induction term
5	Toroidal induction term
8	Poloidal diffusion term
9	Toroidal diffusion term
10	Omega effect / toroidal induction term
11	Omega effect
12	Production of the dipole field
13	Production of the axisymmetric dipole field

```
>>> # To stack all the dtBrms.TAG files of the current directory
>>> ts = MagicTs(field='dtBrms', all=True)
```

8.3.14 perpPar.TAG

Note: This file is **only** written when *l_perpPar=.true*.

This file contains several time series that decompose the kinetic energy into components parallel and perpendicular to the rotation axis. This file is calculated by the subroutine <code>outPerpPar</code>.

No. of column	Contents
1	time
2	Total kinetic energy perpendicular to the rotation axis: $\frac{1}{2}\langle u_s^2 + u_\phi^2 \rangle_V$
3	Total kinetic energy parallel to the rotation axis: $\frac{1}{2}\langle u_z^2\rangle_V$
4	Axisymmetric kinetic energy perpendicular to the rotation axis
5	Axisymmetric kinetic energy parallel to the rotation axis

This file can be read using MagicTs with the following options:

```
>>> # To stack all the perpPar.TAG files of the current directory
>>> ts = MagicTs(field='perpPar', all=True)
```

8.4 Time-averaged radial profiles

8.4.1 eKinR.TAG

This file contains the time and horizontally averaged outer core kinetic energy along the radius. This file is calculated by the subroutine get_e_kin .

No. of col-	Contents
umn	
1	radial level
2	time and horizontally averaged poloidal energy
3	time and horizontally averaged axisymmetric poloidal energy
4	time and horizontally averaged toroidal energy
5	time and horizontally averaged axisymmetric toroidal energy
6	time and horizontally averaged poloidal energy, normalized by surface area at this ra-
	dial level
7	time and horizontally averaged axisymmetric poloidal energy, normalized by surface
	area at this radial level
8	time and horizontally averaged toroidal energy, normalized by surface area at this radial
	level
9	time and horizontally averaged axisymmetric toroidal energy, normalized by surface
	area at this radial level

```
>>> rad = MagicRadial(field='eKinR')
```

8.4.2 eMagR.TAG

This file contains the time and horizontally averaged outer core magnetic energy along the radius. This file is calculated by the subroutine get_e_mag .

No. of col-	Contents
umn	
1	radial level
2	time and horizontally averaged poloidal energy
3	time and horizontally averaged axisymmetric poloidal energy
4	time and horizontally averaged toroidal energy
5	time and horizontally averaged axisymmetric toroidal energy
6	time and horizontally averaged poloidal energy, normalized by surface area at this ra-
	dial level
7	time and horizontally averaged axisymmetric poloidal energy, normalized by surface
	area at this radial level
8	time and horizontally averaged toroidal energy, normalized by surface area at this radial
	level
9	time and horizontally averaged axisymmetric toroidal energy, normalized by surface
	area at this radial level
10	ratio between time-averaged dipole energy and time-averaged total energy

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='eMagR')
```

8.4.3 parR.TAG

This file contains several time and horizontally averaged flow properties (magnetic Reynolds number, Rossby number, etc.). This file is calculated by the subroutine outPar.

No. of col-	Contents
umn	
1	radial level
2	Magnetic Reynolds number
3	Local Rossby number (based on the mass-weighted velocity)
4	Local Rossby number (based on the RMS velocity)
5	Local flow length-scale (based on the mass-weighted velocity)
6	Local flow length-scale based on the non-axisymmetric flow components (based on the mass-weighted velocity)
7	Local flow length-scale (based on the RMS velocity)
8	Local flow length-scale based on the non-axisymmetric flow components (based on the
	RMS velocity)

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='parR')
```

8.4.4 heatR.TAG

Note: This file is only written when an equation for the heat transport (temperature or entropy) is solved.

This file contains several time and horizontally averaged thermodynamic properties (temperature, pressure, entropy, etc.). This file is calculated by the subroutine <code>outHeat</code>.

No. of column	Contents
1	radial level
2	entropy (spherically-symetric contribution)
3	temperature (spherically-symetric contribution)
4	pressure (spherically-symetric contribution)
5	density (spherically-symetric contribution)
6	chemical composition (spherically-symetric contribution)

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='heatR')
```

8.4.5 powerR.TAG

Note: This file is **only** written when $l_power=.true$.

This file contains the time and horizontally averaged power input (Buoyancy power) and outputs (viscous and Ohmic heating). This file is calculated by the subroutine *get_power*.

No. of column	Contents
1	radial level
2	Buoyancy power: $Ra g(r) \langle u_r T' \rangle_s$
3	Chemical power: $Ra_{\xi} g(r) \langle u_r \xi' \rangle_s$
4	Viscous dissipation: $\langle (\sigma)^2 \rangle_s$
5	Ohmic dissipation: $\langle (\nabla \times B)^2 \rangle_s$
6	Standard deviation of buoyancy power
7	Standard deviation of chemical power
8	Standard deviation of viscous dissipation
9	Standard deviation of ohmic dissipation

```
>>> rad = MagicRadial(field='powerR')
```

8.4.6 fluxesR.TAG

Note: This file is **only** written when $l_fluxProfs=.true$.

This file contains the time and horizontally averaged heat flux carried out by several physical processes: conductive flux, convective flux, kinetic flux, viscous flux, Poynting flux and resistive flux. This file is calculated by the subroutine outPar.

No. of column	Contents
1	radial level
2	conductive flux:
	$\mathcal{F}_{cond} = -\frac{1}{Pr} \kappa \tilde{ ho} \tilde{T} \frac{\partial \langle s \rangle_s}{\partial r}$
3	convective flux:
	$\mathcal{F}_{conv} = \tilde{\rho}\tilde{T}\langle s u_r \rangle_s + \frac{Pr Di}{E Ra} \langle p u_r \rangle_s$
4	kinetic flux:
	$\mathcal{F}_{kin} = \frac{1}{2} \frac{Pr Di}{Ra} \langle u_r(\tilde{\rho}u^2) \rangle_s$
5	viscous flux:
	$\mathcal{F}_{visc} = -rac{PrDi}{Ra}\langle m{u}\cdot S angle_s$
6	Poynting flux:
	$\mathcal{F}_{poyn} = -rac{PrDi}{RaEPm}\langle(oldsymbol{u} imesoldsymbol{B} angle_s$
7	resistive flux:
	$\mathcal{F}_{poyn} = \frac{Pr Di}{Ra E Pm^2} \langle (\boldsymbol{\nabla} \times \boldsymbol{B}) \times \boldsymbol{B} \rangle_s$

```
>>> rad = MagicRadial(field='fluxesR')
```

8.4.7 bLayersR.TAG

Note: This file is **only** written when $l_viscBcCalc=.true$.

This file contains several time and horizontally averaged profiles that can be further used to determine thermal and viscous boundary layers: entropy (or temperature), entropy variance, horizontal velocity, radial derivative of the horizontal velocity, thermal dissipation rate. This file is calculated by the subroutine <code>outPar</code>.

No. of column	Contents
1	radial level
2	entropy: $\langle s \rangle_s$
3	entropy variance:
	$\sqrt{\langle (s - \langle s \rangle_s)^2 \rangle_s}$
4	horizontal velocity:
	$u_h = \left\langle \sqrt{u_\theta^2 + u_\phi^2} \right\rangle_s$
5	radial derivative of the horizontal velocity:
	$\partial u_h/\partial r$
6	thermal dissipation rate:
	$\epsilon_T = \langle (\nabla T)^2 \rangle_s$

```
>>> rad = MagicRadial(field='bLayersR')
```

Additional analyses of the boundary layers can then be carried out using BLayers:

```
>>> bl = BLayers(iplot=True)
```

8.4.8 perpParR.TAG

Note: This file is **only** written when $l_perpPar=.true$.

This file contains several time and horizontally averaged profiles that decompose the kinetic energy into components parallel and perpendicular to the rotation axis. This file is calculated by the subroutine <code>outPerpPar</code>.

No. of column	Contents
1	radial level
2	Total kinetic energy perpendicular to the rotation axis:
	$rac{1}{2}\langle u_s^2+u_\phi^2 angle_s$
3	Total kinetic energy parallel to the rotation axis:
	$rac{1}{2}\langle u_z^2 angle_s$
4	Axisymmetric kinetic energy perpendicular to the rotation axis
5	Axisymmetric kinetic energy parallel to the rotation axis

```
>>> rad = MagicRadial(field='perpParR')
```

8.5 Transport properties of the reference state

These files define the radial transport properties of the reference state. These arrays are calculated in the subroutines radial and transportProperties. The output files are written in the subroutine preCalc.

8.5.1 anel. TAG

Note: This output is only calculated when an anelastic model is run, that is when <code>l_anel=.true.</code> or <code>l_anelastic_liquid=.true.</code>.

This file contains the radial profiles of the reference state (density, temperature, gravity, etc.).

No. of column	Contents
1	radial level: r
2	temperature: $\tilde{T}(r)$
3	density: $\tilde{\rho}(r)$
4	radial derivative of the log of the density: $\beta = d \ln \tilde{\rho}/dr$
5	radial derivative of β : $d\beta/dr$
6	gravity: $g(r)$
7	entropy gradient: ds_0/dr
8	thermal diffusion operator: $\nabla \cdot (K(r)\tilde{T}(r)\nabla s_0)$
9	inverse of the Gruneisen parameter :math '1/Gamma': $(\partial \ln \tilde{\rho}/\partial \ln \tilde{T})_S$
10	radial derivative of the log of temperature: $\beta = d \ln \tilde{T}/dr$

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='anel')
>>> # print radius and density
>>> print(rad.radius, rad.rho0)
```

8.5.2 varCond. TAG

Note: This output is only calculated when the electrical conductivity varies with radius, i.e. when $nVarCond \neq 0$

This file contains the radial profiles of the electrical conductivity, the electrical diffusivity and its radial derivative.

No. of column	Contents
1	radial level: r
2	electrical conductivity: $\sigma(r)$
3	electrical diffusivity: $\lambda(r) = 1/\sigma(r)$
4	radial derivative of the electrical diffusivity: $d \ln \lambda / dr$

```
>>> rad = MagicRadial(field='varCond')
>>> print(rad.conduc) # Electrical conductivity
```

8.5.3 varDiff.TAG

Note: This output is only calculated when the thermal diffusivity varies with radius, i.e. when nVarDiff/=0

This file contains the radial profiles of the thermal conductivity, the thermal diffusivity and its radial derivative.

No. of column	Contents
1	radial level: r
2	thermal conductivity: $K(r)$
3	thermal diffusivity: $\kappa(r) = K(r)/\tilde{\rho}(r)$
4	radial derivative of the electrical diffusivity: $d \ln \kappa / dr$
5	Prandtl number: $Pr(r) = \nu(r)/\kappa(r)$

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='varDiff')
>>> print(rad.kappa) # Thermal diffusivity
```

8.5.4 varVisc.TAG

Note: This output is only calculated when the kinematic viscosity varies with radius, i.e. when $nVarVisc \neq 0$

This file contains the radial profiles of the dynamic viscosity, the kinematic viscosity and its radial derivative.

No. of column	Contents
1	radial level: r
2	dynamic viscosity: $\mu(r)$
3	kinetmatic viscosity: $\nu(r) = \mu(r)/\tilde{\rho}(r)$
4	radial derivative of the kinematic viscosity: $d \ln \nu / dr$
5	Prandtl number: $Pr(r) = \nu(r)/\kappa(r)$
6	magnetic Prandtl number $Pm(r) = \nu(r)/\lambda(r)$

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='varVisc')
>>> # print kinematic viscosity and Ekman
>>> print(rad.kinVisc, rad.ekman)
```

8.6 Nonlinear mapping of the Chebyshev grid

8.6.1 rNM. TAG

Note: This file is only written when $l_newmap = .true.$

This file contains the profile of the radial mapping and its derivatives:

No. of column	Contents
1	Grid point index
2	Radius of a grid point
3	First derivative of the mapping at a grid point
4	Second derivative of the mapping at a grid point
5	Third derivative of the mapping at a grid point

8.7 Spectra

8.7.1 kin_spec_#.TAG

This file contains the kinetic energy spectra. This file is written by the subroutine spectrum.

No. of column	Contents
1	degree / order
2	Poloidal kinetic energy versus degree
3	Poloidal kinetic energy versus order
4	Toroidal kinetic energy versus degree
5	Toroidal kinetic energy versus order

This file can be read using MagicSpectrum with the following options:

```
>>> sp = MagicSpectrum(field='ekin')
```

8.7.2 mag_spec_#.TAG

This file contains the magnetic energy spectra. This file is written by the subroutine spectrum.

No. of column	Contents
1	degree / order
2	Poloidal magnetic energy in the outer core versus degree
3	Poloidal magnetic energy in the outer core versus order
4	Toroidal magnetic energy in the outer core versus degree
5	Toroidal magnetic energy in the outer core versus order
6	Poloidal magnetic energy in the inner core versus degree
7	Poloidal magnetic energy in the inner core versus order
8	Toroidal magnetic energy in the inner core versus degree
9	Toroidal magnetic energy in the inner core versus order
10	Poloidal magnetic energy at the CMB versus degree
11	Poloidal magnetic energy at the CMB versus order
12	Poloidal magnetic energy at the CMB

This file can be read using MagicSpectrum with the following options:

```
>>> sp = MagicSpectrum(field='emag')
```

8.7.3 u2_spec_#.TAG

Note: This file is **only** written in an elastic models, i.e. either when *strat/=0* or when *interior_model/="None"*

This file contains the spectra of the square velocity. This file is written by the subroutine spectrum.

No. of column	Contents
1	degree / order
2	Poloidal contribution per degree in the outer core
3	Poloidal contribution per order in the outer core
4	Toroidal contribution per degree in the outer core
5	Toroidal contribution per order in the outer core

This file can be read using MagicSpectrum with the following options:

```
>>> # To read the file ``u2_spec_1.test``:
>>> sp = MagicSpectrum(field='u2', ispec=1, tag='test')
```

8.7.4 T_spec_#.TAG

This file contains the temperature/entropy spectra. It is written by the subroutine <code>spectrum_temp</code>.

No. of column	Contents
1	degree / order
2	RMS temperature/entropy versus degree
3	RMS temperature/entropy versus order
4	RMS temperature/entropy at the ICB versus degree
5	RMS temperature/entropy at the ICB versus order
6	RMS radial derivative of temperature/entropy at the ICB versus degree
7	RMS radial derivative of temperature/entropy at the ICB versus order

8.7.5 2D spectra 2D_[kin|mag]_spec_#.TAG and 2D_[kin|mag]_spec_ave.TAG

Note: Those files are **only** written when $l_2D_spectra=.true.$ The time-averaged files also require that $l_average=.true.$

Those files contain 2-D spectra in the (r,ℓ) and in the (r,m) planes. In other words, the poloidal and toroidal energies versus degree ℓ or versus order m are computed for all radii. There are two kinds of those files that correspond to the aforementioned spectra, namely $2D_kin_spec_\#.TAG$, $2D_mag_spec_\#.TAG$. In case time-averages are requested, $2D_kin_spec_ave.TAG$ and $2D_mag_spec_ave.TAG$ will also be stored. The calculations are done in the subroutine spectrum. The structure of the output files are same for these three outputs. They are stored as fortran unformatted files.

Unformatted files are not directly human readable, and are used to store binary data and move it around without changing the internal representation. In fortran, the open, read and write operations for these files are performed as follows:

```
open(unit=4, file='test', form='unformatted')
read(unit=4) readVar
write(unit=n_out, iostat=ios) writeVar !Unformatted write
```

The structure of the 2D spectra files are as follows:

```
! Line 1
time, n_r_max, l_max, minc ! Time, resolution, max(\ell), azimuthal symmetry
! Line 2
                                                ! Radius
r(1), r(2), r(3), ..., r(n_r_max)
1_____
! Line 3
e_p_1(l=1,r=1), e_p_1(l=1,r=2), ..., e_p_1(l=1,r=n_r_max),
                                                          ! Poloidal
⊶energy
                                                               ! versus
⊶degree
e_p_1(l=l_max,r=1), e_p_1(l=l_max,r=2), ..., e_p_1(l=l_max,r=n_r_max),
! Line 4
e_p_m(m=0,r=1), e_p_1(m=0,r=2), ..., e_p_1(m=1,r=n_r_max),
                                                              ! Poloidal
⇔energy
                                                               ! versus
→order
e_p_1(m=1_max, r=1), e_p_1(m=1_max, r=2), ..., e_p_1(m=1_max, r=n_r_max),
! Line 3
```

8.7. Spectra 107

Those files can be read using the python class MagicSpectrum2D with the following options:

```
>>> # Read the file 2D_mag_spec_3.ext
>>> sp = MagicSpectrum2D(tag='ext', field='e_mag', ispec=3)
>>> # Print e_pol_1 and e_tor_m
>>> print(sp.e_pol_1, sp.e_tor_m)
```

8.7.6 kin_spec_ave.TAG

Note: This file is **only** written when $l_average=.true$.

This file contains the time-average kinetic energy spectra as well as squared quantities to allow a possible further reconstruction of the standard deviation. This file is written by the subroutine <code>spectrum</code>.

No. of column	Contents
1	degree / order
2	Time-averaged poloidal kinetic energy versus degree
3	Time-averaged poloidal kinetic energy versus order
4	Time-averaged toroidal kinetic energy versus degree
5	Time-averaged toroidal kinetic energy versus order
6	Standard deviation of poloidal kinetic energy versus degree
7	Standard deviation of poloidal kinetic energy versus order
8	Standard deviation of toroidal kinetic energy versus degree
9	Standard deviation of toroidal kinetic energy versus order

This file can be read using MagicSpectrum with the following options:

```
>>> # To read the file ``kin_spec_ave.test``:
>>> sp = MagicSpectrum(field='kin', ave=True, tag='test')
```

8.7.7 mag_spec_ave.TAG

Note: This file is **only** written when $l_average=.true$. and the run is magnetic

This file contains the time-average magnetic energy spectra. This file is written by the subroutine spectrum.

No. of column	Contents
1	degree / order
2	Time-averaged poloidal magnetic energy in the outer core versus degree
3	Time-averaged poloidal magnetic energy in the outer core versus order
4	Time-averaged toroidal magnetic energy in the outer core versus degree
5	Time-averaged toroidal magnetic energy in the outer core versus order
6	Time-averaged poloidal magnetic energy at the CMB versus degree
7	Time-averaged poloidal magnetic energy at the CMB versus order
8	Standard deviation of the poloidal magnetic energy in the outer core versus degree
9	Standard deviation of the poloidal magnetic energy in the outer core versus order
10	Standard deviation of the toroidal magnetic energy in the outer core versus degree
11	Standard deviation of the toroidal magnetic energy in the outer core versus order
12	Standard deviation of the magnetic energy at the CMB versus degree
13	Standard deviation of the magnetic energy at the CMB versus order

This file can be read using MagicSpectrum with the following options:

```
>>> # To read the file ``mag_spec_ave.test``:
>>> sp = MagicSpectrum(field='mag', ave=True, tag='test')
```

8.7.8 T_spec_ave.TAG

Note: This file is **only** written when $l_average = .true$.

This file contains the time-averaged temperature/entropy spectra and their standard deviation. It is written by the subroutine spectrum_temp_average.

No. of column	Contents
1	Spherical harmonic degree/order
2	Time-averaged RMS temperature/entropy versus degree
3	Time-averaged RMS temperature/entropy versus order
4	Time-averaged RMS temperature/entropy at the ICB versus degree
5	Time-averaged RMS temperature/entropy at the ICB versus order
6	Time-averaged temperature/entropy gradient at the ICB versus degree
7	Time-averaged temperature/entropy gradient at the ICB versus order
8	Standard deviation of the temperature/entropy versus degree
9	Standard deviation of the temperature/entropy versus order
10	Standard deviation of the temperature/entropy at the ICB versus degree
11	Standard deviation of the temperature/entropy at the ICB versus order
12	Standard deviation of the temperature/entropy gradient at the ICB versus degree
13	Standard deviation of the temperature/entropy gradient at the ICB versus order

8.7. Spectra 109

8.7.9 2D spectra am_[kin|mag]_[pol|tor].TAG

Those files contain the time evolution of the poloidal and toroidal kinetic and magnetic spectra for a given range of spherical harmonic orders m. There are four kinds of those files that correspond to the aforementioned spectra, namely $am_kin_pol.TAG$, $am_kin_tor.TAG$, $am_mag_pol.TAG$ and $am_mag_tor.TAG$. The calculations are done in the subroutine $get_amplitude$. The structure of the output files is the same for the four outputs (fortran unformatted files):

```
!-----
! Line 1
!-----
time(t=0), e_p_m(m=0,t=0), e_p_m(m=1,t=0), ..., e_p_m(m=m_max_modes,t=0)
...
!------
! Line N
!-----
time(t=N), e_p_m(m=0,t=N), e_p_m(m=1,t=N), ..., e_p_m(m=m_max_modes,t=N)
...
```

Those files can be read using the python class MagicTs with the following options:

```
>>> # Read the file am_mag_pol.ext
>>> ts = MagicTs(field='am_mag_pol', tag='ext')
>>> # Print the time
>>> print(ts.time)
>>> # Print the energy content in m=11 for all times
>>> print(ts.coeffs[:, 11])
```

8.8 Graphic files G_#. TAG and G_ave. TAG

These are fortran unformatted files containing 3D data (in the form vector_array(phi, theta, r)) which can be used to visualize the solution. They are written after a fixed number of time steps as specified by the user in the *Output Control namelist* using the parameters listed in the section on *output of graphic files*. In case $l_average$ is set to .true., then an average graphic file, named $G_ave.TAG$, containing time averaged values of 3D data, is also written at the end of the simulation.

These files are written in chunks of latitude for one radial level at a time by the subroutine <code>graphOut</code> or by <code>graphOut_mpi</code> depending on whether <code>USE_MPI</code> is set to Yes or No in the Makefile. The structure of the file looks like below:

```
!-----
! Line 1
!-----
version !Graphout_version_9 (using MPI without comp. without pressure)
!Graphout_version_10 (using MPI, without comp. with pressure)
!Graphout_version_11 (using MPI, with comp. without pressure)
!Graphout_version_12 (using MPI, with comp. with pressure)
!Graphout_version_5 (without MPI, with pressure and comp.)
!Graphout_version_6 (without MPI, with comp. without pressure)
```

```
!Graphout_version_7 (without MPI, without comp. without pressure)
         !Graphout_version_8 (without MPI, without comp. with pressure)
! Line 2
!----
runid
!----
! Line 3
n_r_ic_max-1, minc, nThetasBs,
                                          ! (Simulation time),
ra, ek, pr, prmag,
                                          !nThetasBs = no. of
radratio, sigma_ratio
                                          !theta blocks
! Line 4
!-----
theta(1:n_theta_max)
!Graphout_version_[9/10/11/12]
! These versions are written when the code uses MPI (USE_MPI=yes). Parallel
! chunks of fields are written for different radial levels. Chunks in theta
! are written in parallel using OpenMP
!----
! Data
!-----
! Block N
1_____
!----
! Line 4 + N
n_r-1, r(n_r)/r(1), n_theta_start, n_theta_stop !Radial index, radius in...
→terms
                                           !of r_cmb, start and stop_
∽of
                                           !the theta block
! Line 4 + (N+1)
sr(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Entropy
```

```
!-----
! Line 4 + (N+2)
vr(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Radial velocity
! Line 4 + (N+3)
vt(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Theta component of...
→velocity
!-----
! Line 4 + (N+4)
vp(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Zonal (phi component) of
                                                !velocity
if (l_chemical_conv):
                                                !If composition is stored
  ! Line 4 + (N+5)
 xir(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !composition
if (l_PressGraph):
                                               !If pressure is stored
 1_____
 ! Line 4 + (N+6/7)
 pr(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !pressure
if (l_mag):
                                                  !For a magnetic run
  ! Line 4 + (N+5/6/7)
 br(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Radial magnetic field
  !-----
  ! Line 4 + (N+6/7/8)
 \verb|bt(1:n_phi_tot, n_theta_start:n_theta_stop, n_r)| ! \textit{Theta component of} \\
                                                  !magnetic field
  ! Line 4 + (N+7/8/9)
 bp(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Zonal (phi component)
```

```
!of magnetic field
1-----
!Graphout_version_[5/6/7/8]
!This version is written when the code does not use MPI (USE_MPI=no).
!Chunks in theta are written in parallel with OpenMP.
1_____
! Data
1_____
!-----
! Block N
1_____
! Line 4 + (N+1)
n_r-1, r(n_r)/r(1), n_theta_start, n_theta_stop
! Each of the following data point is written in a new line
! Entropy
sr(1,n_theta_start,n_r)
                              !n_phi = 1, n_theta = n_theta_start, n_r
sr(2,n_theta_start,n_r)
                              !n_phi = 2, n_theta = n_theta_start, n_r
sr(n_phi_tot,n_theta_start,n_r) !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n_r
sr(n_phi_tot,n_theta_start+1,n_r)
sr(1,n_theta_stop,n_r)
                              !n_phi = 1, n_theta = n_theta_stop, n_r
sr(2,n_theta_stop,n_r)
                              !n_{phi} = 2, n_{theta} = n_{theta_stop}, n_{r}
sr(n_phi_tot,n_theta_stop,n_r)
                             !n_phi = n_phi_tot, n_theta = n_theta_stop,
\hookrightarrow n\_r
! Radial velocity
vr(1,n_theta_start,n_r)
                              !n_phi = 1, n_theta = n_theta_start, n_r
vr(2,n_theta_start,n_r)
                              !n_phi = 2, n_theta = n_theta_start, n_r
vr(n_phi_tot,n_theta_start,n_r)
                              !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n_r
vr(1,n_theta_start+1,n_r)
                              !n_phi = 1, n_theta = n_theta_start+1, n_r
```

```
vr(n_phi_tot,n_theta_start+1,n_r)
. . .
vr(1,n_theta_stop,n_r)
                                !n_phi = 1, n_theta = n_theta_stop, n_r
                                !n_phi = 2, n_theta = n_theta_stop, n_r
vr(2,n_theta_stop,n_r)
vr(n_phi_tot,n_theta_stop,n_r)
                                !n_phi = n_phi_tot, n_theta = n_theta_stop,
\hookrightarrow n_r
! Theta component of velocity
vt(1,n_theta_start,n_r)
                                !n_phi = 1, n_theta = n_theta_start, n_r
vt(2,n_theta_start,n_r)
                                !n_phi = 2, n_theta = n_theta_start, n_r
. . .
vt(n_phi_tot,n_theta_start,n_r)    !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n_r
vt(1,n_theta_start+1,n_r)
                                !n_phi = 1, n_theta = n_theta_start+1, n_r
vt(n_phi_tot,n_theta_start+1,n_r)
vt(1,n_theta_stop,n_r)
                                !n_phi = 1, n_theta = n_theta_stop, n_r
vt(2,n_theta_stop,n_r)
                                !n_phi = 2, n_theta = n_theta_stop, n_r
vt(n_phi_tot,n_theta_stop,n_r)
                                !n_phi = n_phi_tot, n_theta = n_theta_stop,
\hookrightarrow n r
! Zonal (phi component) of velocity
vp(1,n_theta_start,n_r)
                                !n_phi = 1, n_theta = n_theta_start, n_r
vp(2,n_theta_start,n_r)
                                !n_phi = 2, n_theta = n_theta_start, n_r
vp(n_phi_tot,n_theta_start,n_r) !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n_r
vp(n_phi_tot,n_theta_start+1,n_r)
vp(1,n_theta_stop,n_r)
                                !n_phi = 1, n_theta = n_theta_stop, n_r
vp(2,n_theta_stop,n_r)
                                !n_phi = 2, n_theta = n_theta_stop, n_r
vp(n_phi_tot,n_theta_stop,n_r)
                                !n_phi = n_phi_tot, n_theta = n_theta_stop,
\hookrightarrow n_r
if (l_chemical_conv):
                                !If chemical composition is stored
! Composition
                                !n_phi = 1, n_theta = n_theta_start, n_r
xi(1,n_theta_start,n_r)
xi(2,n_theta_start,n_r)
                                !n_phi = 2, n_theta = n_theta_start, n_r
xi(n_phi_tot,n_theta_start,n_r) !n_phi = n_phi_tot, n_theta = n_theta_
\hookrightarrowstart, n_r
```

```
xi(1,n_theta_start+1,n_r)
                                 !n_phi = 1, n_theta = n_theta_start+1, n_r
xi(n_phi_tot,n_theta_start+1,n_r)
                                 !n_phi = 1, n_theta = n_theta_stop, n_r
xi(1,n_theta_stop,n_r)
xi(2,n_theta_stop,n_r)
                                 !n_phi = 2, n_theta = n_theta_stop, n_r
xi(n_phi_tot,n_theta_stop,n_r)    !n_phi = n_phi_tot, n_theta = n_theta_stop,
\hookrightarrow n r
if (l_PressGraph):
                                 !If pressure is stored
1_____
! Pressure
pr(1,n_theta_start,n_r)
                                 !n_phi = 1, n_theta = n_theta_start, n_r
pr(2, n_theta_start, n_r)
                                 !n_phi = 2, n_theta = n_theta_start, n_r
pr(n_phi_tot,n_theta_start,n_r)
                                 !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n r
pr(1,n_theta_start+1,n_r)
                                 !n_phi = 1, n_theta = n_theta_start+1, n_r
pr(n_phi_tot,n_theta_start+1,n_r)
pr(1,n_theta_stop,n_r)
                                  !n_phi = 1, n_theta = n_theta_stop, n_r
pr(2,n_theta_stop,n_r)
                                 !n_phi = 2, n_theta = n_theta_stop, n_r
                                 !n_phi = n_phi_tot, n_theta = n_theta_stop,
pr(n_phi_tot,n_theta_stop,n_r)
\hookrightarrow n\_r
if (l_mag):
                                 !Only if it is a magnetic case
! Radial magnetic field
1_____
br(1,n_theta_start,n_r)
                                 !n_phi = 1, n_theta = n_theta_start, n_r
br(2,n_theta_start,n_r)
                                  !n_phi = 2, n_theta = n_theta_start, n_r
. . .
                                 !n_phi = n_phi_tot, n_theta = n_theta_
br(n_phi_tot,n_theta_start,n_r)
⇔start, n_r
br(1,n_theta_start+1,n_r)
                                 !n_phi = 1, n_theta = n_theta_start+1, n_r
br(n_phi_tot,n_theta_start+1,n_r)
br(1,n_theta_stop,n_r)
                                 !n_phi = 1, n_theta = n_theta_stop, n_r
br(2,n_theta_stop,n_r)
                                 !n_{phi} = 2, n_{theta} = n_{theta_stop}, n_{r}
br(n_phi_tot,n_theta_stop,n_r)
                                 !n_phi = n_phi_tot, n_theta = n_theta_stop,
\hookrightarrow n_r
! Theta component of magnetic field
```

```
bt(1,n_theta_start,n_r)
                                !n_phi = 1, n_theta = n_theta_start, n_r
bt(2,n_theta_start,n_r)
                               !n_phi = 2, n_theta = n_theta_start, n_r
bt(n_phi_tot,n_theta_start,n_r)
                               !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n_r
bt(1,n_theta_start+1,n_r)
                               !n_phi = 1, n_theta = n_theta_start+1, n_r
bt(n_phi_tot,n_theta_start+1,n_r)
                               !n\_phi = 1, n\_theta = n\_theta\_stop, n\_r
bt(1,n_theta_stop,n_r)
bt(2,n_theta_stop,n_r)
                               !n_phi = 2, n_theta = n_theta_stop, n_r
! Zonal (phi component) of magnetic field
bp(1,n_theta_start,n_r)
                               !n_phi = 1, n_theta = n_theta_start, n_r
bp(2,n_theta_start,n_r)
                               !n_phi = 2, n_theta = n_theta_start, n_r
bp(n_phi_tot,n_theta_start,n_r)
                              !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n_r
bp(1,n_theta_start+1,n_r)
                               !n_phi = 1, n_theta = n_theta_start+1, n_r
bp(n_phi_tot, n_theta_start+1, n_r)
                               !n_phi = 1, n_theta = n_theta_stop, n_r
bp(1,n_theta_stop,n_r)
bp(2,n_theta_stop,n_r)
                               !n_phi = 2, n_theta = n_theta_stop, n_r
bp(n_phi_tot, n_theta_stop, n_r) !n_phi = n_phi_tot, n_theta = n_theta_stop,
\hookrightarrow n_r
!Subsequent blocks
!Block N+1 in both cases have data at the same radial level but the next
!theta chunk (n_theta_start + nThetaB, n_theta_stop + n_thetaB)
!After data for all the theta blocks have been written for one radial
!level, everything above is repeated for the next radial level
```

The graphic files can be read using the python class MagicGraph.

```
>>> gr = MagicGraph(ivar = 1, tag='TAG')
>>> # print radial velocity
>>> print(gr.vr)
```

They can be visualized using the *Surf* class:

```
>>> s = Surf(tag='TAG')
>>> # Surface map of radial velocity:
>>> s.surf(field = 'vr', r = 0.5, cm = 'jet', levels = 50)
>>> s.slice(field = 'br', lon_0 = [0]) # Longitudinal Slice of radial magnetic field
```

```
>>> s.equat(field = 'entropy') # Equatorial slice of entropy
```

8.9 Movie files *_mov.TAG

Note: These files are written **only** when $l_movie = .true$. or when a finite number of movie frames are asked for using the input parameters described in the *standard inputs section* of the *output control namelist*.

These are unformatted fortran files containing time evolution of fields on different surfaces - constant radius, colatitude or azimuth or on the full 3D grid. The fields can be of various types like radial magnetic field or velocity, entropy, helicity etc. The type of field and the type of surface can be specified using a string that begins with the field name, followed by the surface type (or 'full 3D', when a 3D movie is desired). One such example is as follows:

```
l_movie = .true.,
n_movie_frames = 1000,
movie(1) = "B r r=0.5",
movie(2) = "V all 3D",
movie(3) = "Hel Eq"
```

The code does not interpret any whitespaces and is not case-sensitive so there's no difference between, say, B r cmb and brcmb. For further details and a list of keywords for different fields and surfaces, please refer to the *movie* in the *output control namelist*.

These files are written by the subroutine write_movie_frame.

The movie files are suitably named to reflect the type of field and surface. Their names begin with the keyword for the type of movie asked for, followed by the type of surface, followed by the word 'mov'. Thus, a generic movie name looks like:

```
Keyword_SurType_mov.TAG
```

E.g. if one asks for the radial component of magnetic field on surface of CMB, the movie would be named as Br_CMB_mov.TAG.

When asks multiple movies for same surface types but different surface levels, the surfaces are numbered with integers. Thus, for the following namelist input,

```
l_movie = .true.,
n_movie_frames = 1000,
movie(1) = "B r r=0.5",
movie(2) = "V p r=0.5",
movie(3) = "V r r=0.8",
```

one would get the following movie files as output:

```
Br_R=C1_mov.TAG
Vp_R=C1_mov.TAG
Vr_R=C2_mov.TAG
```

The structure of a generic movie file is as follows:

```
!-----
! Line 1
!-----
```

```
!Movie version: 'JW_Movie_Version_2'
version
! Line 2
!----
n_type, n_surface, !Type of movie, const, n_fields !Type of surface (r,theta,phi,CMB,Eq etc.)
!----
! Line 3
1_____
n_movie_field_type(1:n_fields, n_movie) !Type of fields (velocity,
                                            !mag field, vorticity etc.)
! Line 4
!----
runid
! Line 5
!----
n_r_mov_tot, n_r_max, !Total number of
n_theta_max, n_phi_max, !radial grid points (including IC),
minc, ra, ek, pr, prmag, !grid data, physical parameters
radratio, tScale
!----
! Line 6
{\tt r\_mov\_tot(1:n\_r\_mov\_tot)/r\_cmb} \ {\tt !All \ radii \ in \ terms \ of \ r\_CMB}
! Line 7
1_____
! Line 8
phi(1:n_phi_max)
                                 !All phi points
!----
! Frame N
! Line 8 + N
!----
```

```
n_frame, t_movie(N), omega_ic, omega_ma, dipLat, dipLon, dipStr, dipStrGeo
! Line 8 + (N+1)
frame_data(1:n_fields,n_start:n_stop) !Desired field data on a
                                     !surface or 3D volume
                                     !n_start = start index of a field
                                     !n\_stop = last index of a field
1_____
! Frame N+1
1_____
!----
! Line 8 + (N+2)
n_frame, t_movie(N+1), omega_ic, omega_ma, dipLat, dipLon, dipStr, dipStrGeo
! Line 8 + (N+3)
frame_data(1:n_fields,n_start:n_stop) !Desired field data on a
                                     !surface or 3D volume
                                     !n_start = start index of a field
                                     !n_stop = last index of a field
. . .
1-----
! Frame N+M
                                   !M is the desired number of movie
→frames
1_____
! Line 8 + (N+M)
1_____
n_frame, t_movie(N+M), omega_ic, omega_ma, dipLat, dipLon, dipStr, dipStrGeo
!----
! Line 8 + (N+M)
1_____
frame_data(1:n_fields,n_start:n_stop) !Desired field data on a
                                     !surface or 3D volume
                                     !n_start = start index of a field
                                     !n_stop = last index of a field
```

The 2D movie files can be read and displayed using the python class Movie as follows:

```
>>> Movie() #Lists out available movie files to choose from
>>> M = Movie(file = 'Vr_R=C1_mov.TAG')
```

The 3D movie files can be read using the python class Movie3D:

```
>>> M = Movie3D(file = 'V_3D_mov.TAG')
```

8.10 Restart files checkpoint_*.TAG

Note: These frequency of writing these files are determined by the standard inputs mentioned in the section on *restart* files in the *output control namelist*. If nothing is specified then, by default one restart file is written at the end of the run.

Note: A restart file is read **only** when $l_start = .true$.

These are unformatted fortran files containing a snapshot of information about spectral coefficients and physical and grid parameters. As the name suggests, these files are used to 'restart' a run from a specific time. One such file is read by the code at the beginning and are used as initial conditions for the run. These are very useful for continuing a simulation for a long time on computing clusters where the time for a single run is limited.

The file to be read at the beginning is specified by the input parameter *start_file* which takes in a string providing path to the file.

These files are written by the subroutine store.

The following notations will be used for the coefficients of potentials (note that scalar fields like temperature and pressure do not have a poloidal/toroidal decomposition):

Field	Poloidal	Toroidal
Magnetic	b	aj
Velocity	W	Z
Temperature	S	
Pressure	р	

Time derivatives are denoted with a self-explanatory notation, e.g., dbdt is the first derivative of b.

The word Last appended to a variable name denotes that the value is of the time-step previous to the one during which the file is being written. They are needed for the time-stepping schemes.

_ic with a variable name says that it belongs to the Inner Core.

```
! Line 3
   dsdtLast, dwdtLast, dzdtLast, dpdtLast
else:
!----
! Line 2
  w,z,p
!----
! Line 3
  dwdtLast, dzdtLast, dpdtLast
if (l_mag):
                                                !If magnetic run
! Line 4
1-----
 b, aj, dbdtLast, djdtLast
if(l_mag .and. l_cond_ic):
                                                !If magnetic run
                                                !and conducting inner core
1----
! Line 5
 b_ic, aj_ic, dbdt_icLast, djdt_icLast
! Line 4 or 5 or 6 depending on 1_mag and 1_cond_ic
lorentz_torque_icLast, lorentz_torque_maLast, !Information about torques,
\verb|omega_ic1|, \verb|omega0sz_ic1|, \verb|t0mega_ic1|, | || \textit{!prescribed rotation and}|
                                              !oscillation rates,
omega_ic2, omegaOsz_ic2, tOmega_ic2,
omega_ma1, omegaOsz_ma1, tOmega_ma1,
                                              !and the time step-size
omega_ma2, omegaOsz_ma2, tOmega_ma2,
dtNew
```

8.11 Poloidal and toroidal potentials at given depths

These are fortran unformatted files which store time series of poloidal and toroidal coefficients of different fields (magnetic field, velocity and temeperature) at specific depths.

In the following, time (j) is the time during the j^{th} time step, time (N) being the last step. real and imag denote real and imaginary parts, respectively, of spherical harmonic coefficients. Also, the following notations will be used for

the coefficients of potentials (note that scalar fields like temperature do not have a poloidal/toroidal decomposition):

Field	Poloidal	Toroidal
Magnetic	b	aj
Velocity	W	Z
Temperature	S	

First and second derivatives are denoted with a differential notation. e.g. dw is the first derivative of w, while ddb is the second derivative of b.

8.11.1 B coeff cmb. TAG

Note: This file is **only** written when $l_cmb_field=.true$.

This file contains time series of spherical harmonic coefficients for the poloidal potential of the magnetic field at the outer boundary (CMB) up to a spherical harmonic degree given by l_max_cmb . The detailed calculations are done in the subroutine $write\ Bcmb$. The contents of the file look as follows:

- **Header** The file header consists of the information: l_max_cmb , minc and the number of data points n_data .
- Data Each chunk of data after the header has the same pattern of time followed by a list of real and imaginary values of coefficients.

Thus, on a whole, the structure of the file looks like follows:

This file can be read using MagicCoeffCmb with the following options:

```
>>> # To stack the files B_cmb_coeff.testc to B_cmb_coeff.testf
>>> cmb = MagicCoeffCmb(tag='test[c-f]')
>>> # print Gauss coefficient for (\ell=10, m=3)
>>> print(cmb.glm[:, 10, 3])
```

8.11.2 Coefficients at desired radii

The following files [BIVIT]_coeff_r#.TAG save coefficients at specified depths and are written by the subroutine $write_coeff_r$. See the section on *CMB* and radial coefficients in the ouput control namelist for details of specifying depth, using n_r_step or n_r_array and desired maximum degree of output l_max_r . A separate file for each desired radius is written, numbered suitably as $\lceil B \mid V \mid T \rceil$ coeff r1.TAG, $\lceil B \mid V \mid T \rceil$ coeff r2.TAG etc.

8.11.3 B_coeff_r#.TAG

Note: This file is **only** written when $l_r_{field} = .true$..

This file contains output of time series of the spherical harmonic coefficients of the poloidal and toroidal magnetic field potentials and the first and second derivatives of the poloidal potential coefficients in the order b, db, aj and ddb. The output is for a specific radius, r up to degree l_max_r .

- **Header** The file header consists of the information: l_max_r , minc, the number of data points n_data and the radius, r.
- Data Each chunk of data after the header contains the time at which the coefficients are stored, followed by the real and imaginary parts of: the poloidal coefficient b, it's first derivative db, the toroidal coefficient a j and the second derivative of the poloidal coefficient ddb.

The complete structure of the file looks like follows:

```
real (aj(1=2, m=0)), imag(aj(1=2, m=0)),
real(aj(l=1_max_cmb, m=1_max_cmb)), imag(aj(l=1_max_cmb, m=1_max_cmb)),
real (ddb (l=1, m=0)), imag (ddb (l=1, m=0)),
real (ddb (l=1, m=0)), imag (ddb (l=1, m=0)),
real (ddb (1=1_max_cmb, m=1_max_cmb)), imag (ddb (1=1_max_cmb, m=1_max_cmb)),
. . .
1_____
! Line N + 1
time(N),
real (b(l=1, m=0)), imag(b(l=1, m=0)),
real (b (1=2, m=0)), imag (b (1=2, m=0)),
real (b(1=1_max_cmb, m=1_max_cmb)), imag(b(1=1_max_cmb, m=1_max_cmb)),
real (db(1=1, m=0)), imag(db(1=1, m=0)),
real (db(1=2, m=0)), imag(db(1=2, m=0)),
real(db(l=l_max_cmb, m=l_max_cmb)), imag(db(l=l_max_cmb, m=l_max_cmb)),
real(aj(l=1, m=0)), imag(aj(l=1, m=0)),
real (aj(1=2, m=0)), imag(aj(1=2, m=0)),
real(aj(l=1_max_cmb, m=1_max_cmb)), imag(aj(l=1_max_cmb, m=1_max_cmb)),
real (ddb(1=0, m=0)), imag(ddb(1=0, m=0)),
real (ddb(1=1, m=0)), imag(ddb(1=1, m=0)),
real(ddb(l=l_max_cmb, m=l_max_cmb)), imag(ddb(l=l_max_cmb, m=l_max_cmb))
```

This file can be read using MagicCoeffR with the following options:

```
>>> # To stack the files B_coeff_r3.test* from the working directory
>>> cr = MagicCoeffR(tag='test*', field='B', r=3)
>>> # print the time and the poloidal potential for (\ell=3, m=3)
>>> print(cr.time, cr.wlm[:, 3, 3])
```

8.11.4 V coeff r#.TAG

Note: This file is **only** written when $l_r_{field} = .true$.

This file contains output of time series of the spherical harmonic coefficients of the poloidal and toroidal velocity field potentials and the first derivatives of the poloidal potential coefficients in the order w, dw, and z. The output is for a specific radius, r up to degree l_max_r .

- **Header** The file header consists of the information: l_max_r , minc, the number of data points n_data and the radius. r.
- Data Each chunk of data after the header contains the time at which the coefficients are stored, followed by the real and imaginary parts of: the poloidal coefficient w, it's first derivative dw and the toroidal coefficient z.

The complete structure of the file looks like follows:

```
1_____
! Line 1
l_max_r, minc, n_data, r
1_____
! Line j + 1
/_____
time(j),
real (w(l=1, m=0)), imag (w(l=1, m=0)),
real (w(1=2, m=0)), imag (w(1=2, m=0)),
real (w(1=1_max_cmb, m=1_max_cmb)), imag(w(1=1_max_cmb, m=1_max_cmb)),
real (dw(1=1, m=0)), imag (dw(1=1, m=0)),
real (dw(1=2, m=0)), imag (dw(1=2, m=0)),
real (dw(l=1_max_cmb, m=1_max_cmb)), imag(dw(l=1_max_cmb, m=1_max_cmb)),
real (z(1=1, m=0)), imag(z(1=1, m=0)),
real (z(1=2, m=0)), imag(z(1=2, m=0)),
real(z(l=l_max_cmb, m=l_max_cmb)), imag(z(l=l_max_cmb, m=l_max_cmb)),
. . .
! Line N + 1
time(N),
real (w(l=1, m=0)), imag (w(l=1, m=0)),
real (w(1=2, m=0)), imag(w(1=2, m=0)),
real(w(l=l_max_cmb, m=l_max_cmb)), imag(w(l=l_max_cmb, m=l_max_cmb)),
real (dw(1=1, m=0)), imag(dw(1=1, m=0)),
real (dw(1=2, m=0)), imag (dw(1=2, m=0)),
real (dw(l=1_max_cmb, m=1_max_cmb)), imag(dw(l=1_max_cmb, m=1_max_cmb)),
real (z(1=1, m=0)), imag(z(1=1, m=0)),
real (z(1=2, m=0)), imag(z(1=2, m=0)),
real(z(l=l_max_cmb, m=l_max_cmb)), imag(z(l=l_max_cmb, m=l_max_cmb))
```

This file can be read using MagicCoeffR with the following options:

```
>>> # To stack the files V_coeff_r3.test* from the working directory
>>> cr = MagicCoeffR(tag='test*', field='V', r=3)
>>> # print the poloidal and toroidal potentials for (\ell=6, m=0)
>>> print(cr.wlm[:, 6, 0], cr.zlm[:, 6, 0])
```

8.11.5 T_coeff_r#.TAG

Note: This file is **only** written when $l_r_{field}T = .true$.

This file contains output of time series of the spherical harmonic coefficients of the temperature (or entropy) field. The output is for a specific radius, r up to degree l_max_r .

- **Header** The file header consists of the information: l_max_r , minc, the number of data points n_data and the radius, r.
- Data Each chunk of data after the header contains the time at which the coefficients are stored, followed by the real and imaginary parts of the coefficient s.

The complete structure of the file looks like follows:

8.12 TO outputs

Note: These output files are **only** written when $l_TO=.true$.

8.12.1 TOZ_#.TAG and TOZM.TAG

8.12.2 TO_mov.TAG files

Note: This file is **only** written when $l_TOmovie = .true$.

This file contains the time evolution of the different forces that enter the phi-average of the azimuthal component of the Navier-Stokes equation. This is a special kind of *movie file* that contains seven different azimuthally-averaged fields in a (r,θ) plane: the axisymmetric zonal flow component, the azimuthal component of the Reynolds stresses, the azimuthal component of advection, the azimuthal component of viscosity, the azimuthal component of Lorentz force, the azimuthal component of Coriolis force and the azimuthal component of the time-derivative. The structure of the file is similar to a *movie file*, i.e. an unformatted fortran binary file with a header that describes the type of the movie file. The detailed calculations can be found in the subroutine out TO.

On a whole, the structure of the file looks like follows:

```
1_____
! Line 1
version
! Line 2
n_type, n_surface, const, n_fields
1_____
! Line 3
runid
! Line 4
n_r_movie_max, n_r_max, n_theta_max, n_phi_tot, minc, ra, ek, pr,
prmag, radratio, tScale
!----
! Line 5
r(1), r(2), ..., r(n_r_movie_max)
! Line 6
theta(1), theta(2), ..., theta(n_theta_max)
! Line 7
```

8.12. TO outputs 127

```
phi(1), phi(2), ..., phi(n_theta_max)
. . .
1_____
! Line 7+N
n_frame, t_movie(N), omega_ic, omega_ma, dipLat, dipLon, dipStr, dipStrGeo
! Line 7+(N+1)
vphi(t=t_movie(N),phi=1,theta=1),
vphi(t=t_movie(N),phi=1,theta=2),
vphi(t=t_movie(N),phi=n_phi_max,theta=n_theta_max)
! Line 7+(N+2)
rey(t=t_movie(N),phi=1,theta=1),
rey(t=t_movie(N), phi=1, theta=2),
rey(t=t_movie(N),phi=n_phi_max,theta=n_theta_max)
. . .
! Line 7+(N+7)
dtVphi(t=t_movie(N),phi=1,theta=1),
dtVphi(t=t_movie(N),phi=1,theta=2),
dtVphi(t=t_movie(N),phi=n_phi_max,theta=n_theta_max)
```

This file can be read using TOMovie with the following options:

```
>>> # To load 'TO_mov.test' and time-average it:
>>> to = TOMOvie(file='TO_mov.test', avg=True, levels=65, cm='seismic')
```

8.13 Radial spectra rB[r|p]Spec.TAG

Note: This files are **only** written when *l rMagSpec=.true*.

Those files contain the time-evolution of the poloidal (**rBrSpec.TAG**) and the toroidal (**rBpSpec.TAG**) magnetic energies for all radii including the inner core and for spherical harmonic degrees from $\ell=1$ to $\ell=6$. The calculations are done in the subroutines rBrSpec and rBpSpec, respectively. The outputs are stored as a fortran unformatted file which follows the following structure for rBrSpec. TAG:

The rBpSpec. TAG files have exactly the same structure (just replacing the poloidal energy by its toroidal counterpart).

Warning: Be careful that in this file, n_r_t is the **total** number of grid points (thus including the inner core).

Those files can be read using the python class MagicRSpec with the following options:

```
>>> # Read the files BrSpec.testa, BrSpec.testb and BrSpec.testc and stack them
>>> rsp = MagicRSpec(tag='test[a-c]', field='Br')
>>> # Print time and the time evolution of e_pol(\ell=4) at the 10th radial grid point
>>> print(rsp.time, rsp.e_pol[:, 10, 3])
```

8.14 Potential files [V|B|T]_lmr_#.TAG

8.14.1 V_lmr_#.TAG and V_lmr_ave.TAG

Note: These output files are **only** written when either when $l_storePot=.true$. or when $l_storeVpot=.true$.

These files contain a snapshot of the poloidal and toroidal flow potentials w and z in the radial space for all spherical harmonic degrees and orders. They basically contain two arrays of dimension (lm_max , n_r_max). The detailed calculations are done in the subroutine $write_Pot$. The outputs are stored as a fortran unformatted file which follows the following structure:

```
!-----
! Line 1
! Line 2
ra, ek, pr, prmag, sigma_ratio, omega_ma, omega_ic ! Header (physics)
!-----
! Line 3
time
                                           ! Header (time)
!----
! Line 4
!-----
r(1), ..., r(n_r_max),rho0(1), ..., rho0(n_r_max) ! Radius, Density
! Line 5
                                           ! Poloidal potential
w(lm=1, n_r=1), w(lm=2, n_r=1), ..., w(lm=lm_max, n_r=1),
w(lm=1, n_r=n_r_max), \ldots, w(lm=lm_max, n_r=n_r_max)
1_____
! Line 6
                                           ! Toroidal potential
z(lm=1, n_r=1), z(lm=2, n_r=1), ..., z(lm=lm_max, n_r=1),
z(lm=1,n_r=n_r_max), ..., z(lm=lm_max,n_r=n_r_max)
```

The potential files that contain the poloidal and toroidal potentials for the momentum can be read and transformed to the physical space using the python class <code>MagicPotential</code>.

```
>>> p = MagicPotential(field='V')
>>> print(p.pol[p.idex[3,2], 32]) # print w(1=3, m=2, n_r=32)
```

Once transformed to the physical space using a Fourier and a Legendre transform, they can be displayed:

```
>>> p.equat(field='vr', cm='jet', levels=50) # Equatorial cut of vr
>>> p.avg(field='vp') # Azimuthal average of vphi
>>> p.surf(field='vt', r=0.8) # Radial cut of vtheta at r=0.8r_o
```

8.14.2 B_lmr_#.TAG, B_lmr_ave.TAG

Note: These output files are **only** written when either when $l_storePot=.true$. or when $l_storeBpot=.true$.

These files contain a snapshot of the poloidal and toroidal magnetic potentials b and a j in the radial space for all spherical harmonic degrees and orders. The detailed calculations are done in the subroutine $write_Pot$. The outputs are stored as a fortran unformatted file which follows the following structure:

```
! Line 1
l_max, n_r_max, n_r_ic_max, minc, lm_max
                                            ! Header (truncation)
! Line 2
1_____
ra, ek, pr, prmag, sigma_ratio, omega_ma, omega_ic ! Header (physics)
! Line 3
time
                                                ! Header (time)
1_____
! Line 4
r(1), ..., r(n_r_max),rho0(1), ..., rho0(n_r_max) ! Radius, Density
!----
! Line 5
                                                ! Poloidal potential
b(lm=1, n_r=1), b(lm=2, n_r=1), ..., b(lm=lm_max, n_r=1),
b(lm=1, n_r=n_r_max), ..., b(lm=lm_max, n_r=n_r_max)
! Line 6
1_____
                                                ! Toroidal potential
aj(lm=1, n_r=1), aj(lm=2, n_r=1), ..., aj(lm=lm_max, n_r=1),
\label{eq:aj(lm=1,n_r=n_r_max), ..., aj(lm=lm_max,n_r=n_r_max)} aj(lm=1,n_r=n_r_max), ..., aj(lm=lm_max,n_r=n_r_max)
! The two following lines are optional and are only written when there is !
! an electrically-conducting inner-core
! Line 7
1_____
```

The potential files that contain the poloidal and toroidal potentials for the magnetic field can be read and transformed to the physical space using the python class MagicPotential.

```
>>> p = MagicPotential(field='B')
>>> print(p.tor[p.idex[3,2], 32]) # print aj(1=3, m=2, n_r=32)
```

Once transformed to the physical space using a Fourier and a Legendre transform, they can be displayed:

```
>>> p.equat(field='Br', cm='jet', levels=50) # Equatorial cut of Br
>>> p.avg(field='Bp') # Azimuthal average of Bphi
>>> p.surf(field='Bt', r=0.8) # Radial cut of Btheta at r=0.8r_o
```

8.14.3 T_lmr_#.TAG, T_lmr_ave.TAG

Note: These output files are **only** written when either when $l_storePot=.true$. or when $l_storeTpot=.true$.

These files contain a snapshot of the temperature/entropy s in the spectral and radial spaces for all spherical harmonic degrees and orders. They basically contain one array of dimension (lm_max , n_r_max). The detailed calculations are done in the subroutine $write_Pot$. The outputs are stored as a fortran unformatted file which follows the following structure:

```
!------
! Line 4
!------
r(1), ..., r(n_r_max), rho0(1), ..., rho0(n_r_max) ! Radius, Density
!-------
! Line 5
!------
! Line 5
!------
s(lm=1, n_r=1), s(lm=2, n_r=1), ..., s(lm=lm_max, n_r=1),
...
s(lm=1, n_r=n_r_max), ..., s(lm=lm_max, n_r=n_r_max)
```

The potential files that contain the temperature/entropy in the spectral space can be read and transformed to the physical space using the python class <code>MagicPotential</code>.

```
>>> p = MagicPotential(field='T')
>>> print(p.pol[p.idex[0,0], 10]) # print s(l=0, m=0, n_r=10)
```

Once transformed to the physical space using a Fourier and a Legendre transform, they can be displayed:

```
>>> p.equat(field='T', cm='jet', levels=50) # Equatorial cut of temperature/entropy
>>> p.avg(field='T') # Azimuthal average of temperature/entropy
```

DATA VISUALISATION AND POST-PROCESSING

Most of the *output files* written during a run of MagIC can be treated with the python post-processing classes and functions present in the \$MAGIC_HOME/python/magic directory. These classes depend on several python libraries that can be usually found in most of the Linux distributions.

9.1 Requirements

9.1.1 Hard dependencies

- python 2.7/3.3 or higher.
- matplotlib 1.0 or higher.
- scipy 0.10 or higher.

9.1.2 Optional dependencies

- Although entirely optional, the installation of ipython makes the interactive use of the post-processing python functions much more pleasant. Installing it is therefore recommanded for a smoother interactive usage of the python functions.
- The installation of the basemap toolkit is optional. If installed, additional projections for the magic.Surf (Aitoff, orthographic, Mollweide, etc.) class will be provided for 2-D surface plotting. Otherwise, the usage of magic.Surf is limited to the Hammer projection.

9.2 Configuration: magic.cfg file

A file named magic.cfg located in \$MAGIC_HOME/python/magic/magic.cfg should have been created when you used the source path/sourceme.sh command for the first time on your machine. At that stage, it tried to automatically fill the best options that correspond to your setup. Although tested on several various machine configurations, the auto-configuration script might however fail on your setup. The paragraph below details the possible options that you may want to adjust in the magic.cfg file.

9.2.1 Detailed options

In case, the file magic.cfg doesn't exist in the directory \$MAGIC_HOME/python/magic, you can easily copy it from the default configuration magic.cfg.default and then adjust the options manually:

```
$ cp $MAGIC_HOME/python/magic/magic.cfg.default $MAGIC_HOME/python/magic/magic.cfg
```

In that file, you can set up the default matplotlib rendering backend (among the possible options: TkAgg, GTKAgg, Qt4Agg,...). The default configuration is

```
backend = TkAgg
```

Note: This is usually the default configuration which is the most likely to work on supercomputing clusters.

If LaTeX is installed on your work station, you might also want to make use of the better looking LaTeX fonts for all your displayed matplotlib figures (labels, caption, ticks, etc.). Be careful though that most of the time LaTeX is **not installed** on supercomputers. The default configuration is thus:

```
labTex = False
```

You can change the default colormap that will be used in the plotting routines.

```
defaultCm = seismic
```

You cant change the default number of contours that will be used in the plotting routines.

```
defaultLevels = 65
```

If you want to enable all the features of the python functions (faster reading the $G_{-}\#.TAG$, conversion to the VTK/VTS file format, potential extrapolation of the field lines, etc.), some fortran libraries present in the $$MAGIC_HOME/python/magic/fortranLib$$ directory need to be built using the f2py, which should be available on your Linux workstation if all the required python libraries have been correctly installed. The boolean buildlib can control whether you want to try building the fortran libraries with f2py. The following configuration will try to build the libraries:

```
buildLib = True
```

The exact name of the executable f2py however varies from one Linux distribution to the other. Among possible options, one frequently finds: f2py, f2py3. This can be set to your proper configuration using the f2pyexec option of the magic.cfg file. The default configuration is:

```
f2pyexec = f2py2
```

You can also choose the fortran compiler you want to use on your machine. A list of the installed compilers can be obtained by using (where f2py has to be replaced by your own executable):

```
$ f2py -c --help-fcompiler
```

The most frequent options are:

- qnu95 for the GNU gfortran compiler.
- intelem for the Intel ifort compiler.
- pg for the Portlang group pgf compiler.

Once you've decided the ideal configuration for your machine, set it up via the option fcompiler:

```
fcompiler = intelem
```

Finally, he same configuration procedure can be applied to the C compiler using the variable named ccompiler. The possible options are:

- unix for the GNU gcc compiler.
- intelem for the Intelicc compiler.

In most of the configurations, the default configuration should do a good job:

```
ccompiler = unix
```

If you encounter any problem during the building stage, you can try playing with this parameter though.

9.2.2 Ready?!

Once you think you set up your magic.cfg file correctly, you can test your configuration. If you decided to build the fortran libraries (i.e. buildLib=True), you can easily test it with any python shell by typing the following command:

```
>>> from magic import *
```

If the build was successful, it should display:

```
Please wait: building greader_single...
Please wait: building greader_double...
Please wait: building lmrreader_single...
Please wait: building Legendre transforms...
Please wait: building vtklib...
```

Once the libraries have been successfully installed, this message won't be displayed again, except if you remove the *.so files that are now present in the \$MAGIC_HOME/python/magic/directory.

9.3 Python functions and classes

Once the python environment is correctly configured you can use the available functions and classes to analyse and post-process your data. The following pages will give you the detailed API of the available classes, as well as some practical examples:

Python classes

- 1. To read the **log.TAG** files , see *here*.
- 2. To read and analyse the time series, see *here*.
- 3. To read and analyse the radial profiles, see *here*.
- 4. To read and analyse spectra **_spec_#.TAG**, see *here*.
- 5. To read and analyse the **G_#.TAG** files, see *here*.
- 6. To read and analyse movie files **mov.TAG**, see *here*.
- 7. To read and analyse coeff files [VIBIT]_coeff.TAG, see here.
- 8. To read and analyse potential files [VIBIT]_lmr_#.TAG, see here.
- 9. To read and analyse radial spectra **B[rlp]Spec.TAG**, see *here*.

- 10. To read and analyse TO outputs, see *here*.
- 11. To compare several runs simultaneously, see *here*.
- 12. To transform the graphic files **G_#.TAG** to a file format readable by paraview, VisIt or mayavi and do some fancy 3-D visualisation, see *here*.
- 13. For additional diagnostics (boundary layer, heat transport, interpolation on cylindrical grids, etc.), see *here*.
- 14. To take a look at the additional useful functions available (derivation, integration, interpolation, etc.), see *here*.

9.3.1 Support for the log. TAG files

```
class magic.MagicSetup(datadir='.', nml='input.nml', quiet=False)
```

This class allows to read the input namelist or the log file of a current job and creates an object that contains all the parameters found in the namelist/log file.

```
>>> stp = MagicSetup(nml='log.test', quiet=True)
>>> print(stp.ra) # print the Rayleigh number
>>> print(stp.n_r_max) # print n_r_max
```

__init__ (datadir='.', nml='input.nml', quiet=False)

Parameters

- datadir (str) the working directory
- nml (str) name of the input namelist/ log file
- quiet (bool) when set to True, makes the output silent (default False)

9.3.2 Support for the time series

class magic.**MagicTs** (*datadir='.'*, *field='e_kin'*, *iplot=True*, *all=False*, *tag=None*)

This python class is used to read and plot the different time series written by the code:

- Kinetic energy: *e_kin.TAG*
- Magnetic energy of the outer core: e_mag_oc.TAG
- Magnetic energy of the inner core: e_mag_ic.TAG
- Dipole information: dipole.TAG
- Rotation: rot.TAG
- Diagnostic parameters: par.TAG
- Geostrophy: geos.TAG
- Heat transfer: heat.TAG
- Helicity: helicity.TAG
- Velocity square: *u_square.TAG*
- Angular momentum: AM.TAG
- Power budget: power.TAG
- Earth-likeness of the CMB field: earth_like.TAG

- Parallel and perpendicular decomposition: perpPar.TAG
- RMS force balance: dtVrms.TAG
- RMS induction terms: dtBrms.TAG
- Time-evolution of m-spectra: am_[kin|mag]_[pol|tor].TAG

Here are a couple of examples of how to use this function.

```
>>> # plot the most recent e_kin.TAG file found in the directoy
>>> MagicTs(field='e_kin')
>>>
>>> # stack **all** the power.TAG file found in the directory
>>> ts = MagicTs(field='power', all=True)
>>> print(ts.time, ts.buoPower) # print time and buoyancy power
>>>
>>> # If you only want to read the file ``heat.NOm2z``
>>> ts = MagicTs(field='heat', tag='NOm2z', iplot=False)
```

__init__ (datadir='.', field='e_kin', iplot=True, all=False, tag=None)

Parameters

- datadir (str) working directory
- **field** (str) the file you want to plot
- **iplot** (bool) when set to True, display the plots (default True)
- **all** (bool) when set to True, the complete time series is reconstructed by stacking all the corresponding files from the working directory (default False)
- tag (str) read the time series that exactly corresponds to the specified tag

plot()

Plotting subroutines. Only called if 'iplot=True'

9.3.3 Averaging the time series

class magic.AvgField(tstart=None, tag=None, dipExtra=False, perpPar=False, std=False)

This class calculates the time-average properties from time series. It will store the input starting time in a small file named tInitAvg, such that the next time you use it you don't need to give tstart again.

```
>>> # Average from t=2.11 and also store the additional dipole.TAG informations
>>> a = AvgField(tstart=2.11, dipExtra=True)
>>> # Average only the files that match the pattern N0m2[a-c]
>>> a = AvgField(tstart=2.11, tag='N0m2[a-c]')
>>> # Average only the files that match the pattern N0m2Z*
>>> a = AvgField(tstart=2.11, tag='N0m2Z*')
>>> print(a) # print the formatted output
```

___init__ (tstart=None, tag=None, dipExtra=False, perpPar=False, std=False)

Parameters

- tstart (float) the starting time for averaging
- **tag** (str) if you specify an input tag (generic regExp pattern), the averaging process will only happen on the time series that match this input pattern

- dipExtra (bool) if this parameter is set to True, then additional values extracted from dipole.TAG are also computed
- perpPar (bool) additional values extracted from perpPar.TAG are also computed

```
__str__()
Formatted output
```

9.3.4 Support for time-averaged radial profiles

class magic.MagicRadial(datadir='.', field='eKin', iplot=True, tag=None, tags=None, normalize_radius=False)

This class can be used to read and display the time and horizontally averaged files:

- Kinetic energy: eKinR.TAG
- Magnetic energy: eMagR.TAG
- Anelastic reference state: anel.TAG
- Variable electrical conductivity: varCond.TAG
- Variable thermal diffusivity: varDiff.TAG
- Variable kinematic viscosity: varVisc.TAG
- Diagnostic parameters: parR.TAG
- Power budget: powerR.TAG
- Heat fluxes: fluxesR.TAG
- Mean entropy, temperature and pressure: heatR.TAG
- Radial profiles used for boundary layers: bLayersR.TAG
- Parallel/perpendicular decomposition: perpParR.TAG

```
>>> rad = MagicRadial(field='eKinR') # display the content of eKinR.tag
>>> print(rad.radius, rad.ekin_pol_axi) # print radius and poloidal energy
```

__init__ (datadir='.', field='eKin', iplot=True, tag=None, tags=None, normalize_radius=False)

Parameters

- datadir (str) working directory
- field(str) the field you want to plot
- iplot (bool) to plot the output, default is True
- tag(str) a specific tag, default is None
- tags (list) a list that contains multiple tags: useful to sum several radial files

plot()

Display the result when iplot=True

9.3.5 Support for the spectra files (kin|mag|u2)_spec_#.TAG

- Kinetic energy spectra: kin_spec_#.TAG
- Magnetic energy spectra: mag_spec_#.TAG
- Spectra of the velocity square: u2_spec_#.TAG

```
>>> # display the content of kin_spec_1.tag
>>> # where tag is the most recent file in the current directory
>>> sp = MagicSpectrum(field='e_kin', ispec=1)
>>> # display the content of mag_spec_ave.test on one single figure
>>> sp = MagicSpectrum(field='e_mag', tag='test', ave=True, gather=True)
```

init (datadir='.', field='e kin', iplot=True, ispec=None, ave=False, gather=False, tag=None)

Parameters

- **field** (str) the spectrum you want to plot, 'e_kin' for kinetic energy, 'e_mag' for magnetic
- **iplot** (bool) display the output plot when set to True (default is True)
- ispec (int) the number of the spectrum you want to plot
- tag (str) file suffix (tag), if not specified the most recent one in the current directory is chosen
- **ave** (bool) plot a time-averaged spectrum when set to True
- **gather** (bool) gather the spectra on the same figure when set to True, display one figure per spectrum when set to False, (default is False)
- datadir (str) current working directory

plot()

Plotting function

9.3.6 Support for the 2-D spectra files

```
class magic.MagicSpectrum2D (datadir='.', field='e_mag', iplot=True, ispec=None, tag=None, cm='jet', levels=33, precision='Float64', ave=False)

This class can be used to read and display 2-D spectra in the (r,\ell) and in the (r,m) planes
```

- Kinetic energy spectra: 2D_kin_spec_#.TAG
- Velocity square spectra: 2D_u2_spec_#.TAG
- Magnetic energy spectra: 2D_mag_spec_#.TAG

```
>>> # display the content of 2D_kin_spec_1.tag
>>> # where tag is the most recent file in the current directory
>>> sp = MagicSpectrum2D(field='e_kin', ispec=1, levels=17, cm='seismic')
>>> # display the content of 2D_mag_spec_3.test
>>> sp = MagicSpectrum2D(field='e_mag', tag='test', ispec=3)
```

__init__ (datadir='.', field='e_mag', iplot=True, ispec=None, tag=None, cm='jet', levels=33, precision='Float64', ave=False)

- **field** (str) the spectrum you want to plot, 'e_kin' for kinetic energy, 'e_mag' for magnetic
- iplot (bool) display the output when set to True (default is True)

- **ispec** (*int*) the number of the spectrum you want to plot
- tag (str) file suffix (tag=, if not specified the most recent one in the current directory is chosen
- cm (str) name of the colormap (default='jet')
- **levels** (*int*) number of contour levels (default 33)
- **precision** (str) single or double precision
- datadir (str) current working directory
- **ave** (bool) plot a time-averaged spectrum when set to True

plot (levels, cm)

Plotting function

Parameters

- levels (int) number of contour levels
- $\mathbf{cm}(str)$ name of the colormap

9.3.7 Support for G_#.TAG files

```
class magic.MagicGraph(ivar=None, datadir='.', quiet=True, ave=False, tag=None, preci-
sion='Float32')
```

This class allows to read the 3-D graphic outputs of the MagIC code (*G_#.TAG* and *G_*ave.TAG) files. Those are binary unformatted outputs, there are therefore two ways to load them:

- If buildLib=True in magic.cfg and the fortran libraries were correctly built, then the reader uses a fortran program that is expected to be much faster than the pure python routine.
- If buildLib=False, then a pure python program is used to read the G files.

```
>>> # Regular G files
>>> gr = MagicGraph(ivar=1, tag='N0m2a')
>>> print(gr.vr.shape) # shape of vr
>>> print(gr.ek) # print ekman number
>>> print(gr.minc) # azimuthal symmetry
>>> # Averaged G file with double precision
>>> gr = MagicGraph(ave=True, tag='N0m2', precision='Float64')
```

__init__ (ivar=None, datadir='.', quiet=True, ave=False, tag=None, precision='Float32')

Parameters

- ave (bool) when set to True, it tries to find an average G file (G_ave.TAG)
- ivar (int) the number of the G file
- tag (str) extension TAG of the G file. If not specified, the most recent G_#.TAG file found in the directory will be selected.
- quiet (bool) when set to True, makes the output silent
- datadir (str) directory of the G file (default is .)
- **precision** (str) single or double precision (default 'Float32')

rearangeLat (field)

This function is used to unfold the colatitudes

Parameters field (numpy.ndarray) – input array with MagIC ordering of colatitudes (i.e. successively Northern Hemisphere and Southern Hemisphere)

Returns an array with the regular ordering of the colatitudes

Return type numpy.ndarray

class magic.**Surf** (*ivar=None*, *datadir='.'*, *vort=False*, *ave=False*, *tag=None*, *precision='Float32'*)

This class allows to display the content of a graphic file (*G_#.TAG* or *G_ave.TAG*). It allows to plot radial, azimuthal and equatorial cuts as well as phi-averages.

```
>>> # To read G_1.test
>>> s = Surf(ivar=1, ave=False, tag='test')
>>> # To read the latest G file in the working directory (double precision)
>>> s = Surf(precision='Float64')
```

```
>>> # Possible plots
>>> s.equat(field='vr')
>>> s.avg(field='vp')
>>> s.surf(field='entropy', r=0.8)
>>> s.slice(field='Br', lon_0=[0, 30])
```

__init__ (ivar=None, datadir='.', vort=False, ave=False, tag=None, precision='Float32')

Parameters

- ivar (int) index of the graphic file
- **ave** (bool) when set to True, it tries to read a time-averaged graphic file
- tag (str) TAG suffix extension of the graphic file
- **vort** (bool) a boolean to specify whether one wants to compute the 3-D vorticity components (take care of the memory imprint)
- datadir (str) the working directory
- **precision** (*str*) the storage precision of the graphic file (single or double precision). Default is 'Float32' (single)

avg (field='vphi', levels=65, cm=u'seismic', normed=True, vmax=None, vmin=None, cbar=True, tit=True, pol=False, tor=False, mer=False, merLevels=16, polLevels=16)
Plot the azimutal average of a given field.

```
>>> s = Surf()
>>> # Axisymmetric zonal flows, 65 contour levels
>>> s.avg(field='vp', levels=65, cm='seismic')
```

```
>>> # Minimal plot (no cbar, not title)
>>> s.avg(field='Br', tit=False, cbar=False)
```

```
>>> # Axisymmetric Bphi + poloidal field lines
>>> s.avg(field='Bp', pol=True, polLevels=8)
```

```
>>> # Omega-effect, contours truncated from -1e3 to 1e3
>>> s.avg(field='omeffect', vmax=1e3, vmin=-1e3)
```

Parameters

• **field** (str) – the field you want to display

- **levels** (*int*) the number of levels in the contourf plot
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu_r', etc.)
- tit (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.
- pol (bool) diplay the poloidal field lines contours when set to True
- tor (bool) diplay the toroidal axisymmetric field contours when set to True
- mer (bool) display the meridional circulation contours when set to True
- merLevels (int) number of contour levels to display meridional circulation
- pollevels (int) number of contour levels to display poloidal field lines

equat (field='vr', levels=65, cm=u'seismic', normed=True, vmax=None, vmin=None, cbar=True, tit=True, avg=False, normRad=False)
Plot the equatorial cut of a given field

```
>>> s = Surf()
>>> # Equatorial cut of the z-vorticity, 65 contour levels
>>> s.equat(field='vortz', levels=65, cm='seismic')
```

```
>>> # Minimal plot (no cbar, not title)
>>> s.equat(field='bphi', tit=False, cbar=False)
```

```
>>> # Control the limit of the colormap from -1e3 to 1e3
>>> s.equat(field='vr', vmin=-1e3, vmax=1e3, levels=33)
```

```
>>> # Normalise the contour levels radius by radius
>>> s.equat(field='jphi', normRad=True)
```

- **field** (str) the name of the input physical quantity you want to display
- avg (bool) when set to True, an additional figure which shows the radial profile of the input physical quantity (azimuthal average) is also displayed
- normRad (bool) when set to True, the contour levels are normalised radius by radius (default is False)
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu_r', etc.)
- **tit** (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels

- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.
- slice (field='Bphi', lon_0=0.0, levels=65, cm=u'seismic', normed=True, vmin=None, vmax=None, cbar=True, tit=True, grid=False, nGridLevs=16, normRad=False)
 Plot an azimuthal slice of a given field.

```
>>> s = Surf()
>>> # vphi at 0, 30, 60 degrees in longitude
>>> s.slice(field='vp', lon_0=[0, 30, 60], levels=65, cm='seismic')
```

```
>>> # Minimal plot (no cbar, not title)
>>> s.avg(field='vp', lon_0=32, tit=False, cbar=False)
```

```
>>> # Axisymmetric Bphi + poloidal field lines
>>> s.avg(field='Bp', pol=True, polLevels=8)
```

```
>>> # Omega-effect, contours truncated from -1e3 to 1e3
>>> s.avg(field='omeffect', vmax=1e3, vmin=-1e3)
```

- **field** (str) the field you want to display
- lon_0 (float or list) the longitude of the slice in degrees, or a list of longitudes
- levels (int) the number of levels in the contourf plot
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu r', etc.)
- tit (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- grid (bool) display or hide the grid
- nGridLevs (int) number of grid levels
- **normRad** (bool) when set to True, the contour levels are normalised radius by radius (default is False)

surf (field='Bphi', proj='hammer', lon_0=0.0, r=0.85, vmax=None, vmin=None, lat_0=30.0, levels=65, cm=u'seismic', lon_shift=0, normed=True, cbar=True, tit=True, lines=False)
Plot the surface distribution of an input field at a given input radius (normalised by the outer boundary radius).

```
>>> s = Surf()
>>> # Radial flow component at ``r=0.95 r_o``, 65 contour levels
>>> s.surf(field='vr', r=0.95, levels=65, cm='seismic')
```

```
>>> # Minimal plot (no cbar, not title)
>>> s.surf(field='entropyfluct', r=0.6, tit=False, cbar=False)
```

```
>>> # Control the limit of the colormap from -1e3 to 1e3
>>> s.surf(field='vp', r=1., vmin=-1e3, vmax=1e3, levels=33)
```

```
>>> # If basemap is installed, additional projections are available
>>> s.surf(field='Br', r=0.95, proj='ortho', lat_0=45, lon_0=45)
```

- **field** (str) the name of the field you want to display
- **proj** (str) the type of projection. Default is Hammer, in case you want to use 'ortho' or 'moll', then Basemap is required.
- **r** (float) the radius at which you want to display the input data (in normalised units with the radius of the outer boundary)
- levels (int) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu_r', etc.)
- lon_shift (int) translate map in azimuth (in degrees)
- **lon_0** (*float*) central azimuth (only used with Basemap)
- lat_0 (float) central latitude (only used with Basemap)
- tit (bool) display the title of the figure when set to True
- tit display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- **lines** (bool) when set to True, over-plot solid lines to highlight the limits between two adjacent contour levels
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

9.3.8 Support for movie files *_mov.TAG

class magic.Movie (file=None, iplot=True, step=1, png=False, lastvar=None, nvar='all', levels=12, cm='RdYlBu_r', cut=0.5, bgcolor=None, fluct=False, normed=False, avg=False, std=False, dpi=80, normRad=False, precision='Float32', deminc=True, ifield=0)

This class allows to read the movie files generated by the MagIC code.

```
>>> m = Movie()
>>> # This returns a list of the available movies in the directory
>>> # and lets you decide which one you want to read
```

```
>>> # Reads and display AV_mov.test
>>> m = Movie(filed='AV_mov.test')
>>> print(m.data) # access to the data
```

```
>>> # Read three movie files (no display)
>>> m1 = Movie(file='AV_mov.testa', iplot=False)
>>> m2 = Movie(file='AV_mov.testb', iplot=False)
>>> m3 = Movie(file='AV_mov.testc', iplot=False)
>>> # Stack them together
>>> m = m1+m2+m3
```

```
>>> # Display
>>> m.plot(levels=33, cm='seismic', cut=0.5)
```

```
>>> # Store the outputs in movie/img_#.png
>>> # Only from the timesteps 280 to 380
>>> m = Movie(file='AB_mov.test', png=True, nvar=100, lastvar=380)
```

___add___(new)

Built-in function to sum two movies

Note: So far this function only works for two movies with the same grid sizes. At some point, we might introduce grid extrapolation to allow any summation

__init__ (file=None, iplot=True, step=1, png=False, lastvar=None, nvar='all', levels=12, cm='RdYlBu_r', cut=0.5, bgcolor=None, fluct=False, normed=False, avg=False, std=False, dpi=80, normRad=False, precision='Float32', deminc=True, ifield=0)

Parameters

- nvar (int) the number of timesteps of the movie file we want to plot starting from the last line
- png (bool) if png=True, write the png files instead of display
- iplot (bool) if iplot=True, display otherwise just read
- lastvar (int) the number of the last timesteps to be read
- **step** (*int*) the stepping between two timesteps
- **levels** (*int*) the number of contour levels
- $\mathbf{cm}(str)$ the name of the color map
- **fluct** (bool) if fluct=True, substract the axisymmetric part
- **normed** (bool) the colormap is rescaled every timestep when set to True, otherwise it is calculated from the global extrema
- avg (bool) if avg=True, time-average is displayed
- **std** (bool) if std=True, standard deviation is displayed
- **dpi** (*int*) dot per inch when saving PNGs
- normRad (bool) if normRad=True, then we normalise for each radial level
- **precision** (*str*) precision of the input file, Float32 for single precision, Float64 for double precision
- **cut** (float) adjust the contour extrema to max(abs(data))*cut
- **bgcolor** (str) background color of the figure
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry
- **ifield** (*int*) in case of a multiple-field movie file, you can change the default field displayed using the parameter ifield

avgStd (ifield=0, std=False, cut=0.5, levels=12, cmap='RdYlBu_r')
Plot time-average or standard deviation

- **ifield** (*int*) in case of a multiple-field movie file, you can change the default field displayed using the parameter ifield
- std (bool) the standard deviation is computed instead the average when std is True
- **levels** (*int*) number of contour levels
- cmap (str) name of the colormap
- cut (float) adjust the contour extrema to max(abs(data))*cut

Parameters

- **ifield** (*int*) in case of a multiple-field movie file, you can change the default field displayed using the parameter ifield
- levels (int) number of contour levels
- cmap (str) name of the colormap
- cut (float) adjust the contour extrema to max(abs(data))*cut
- png(bool) save the movie as a series of png files when set to True
- **dpi** (*int*) dot per inch when saving PNGs
- **bgcolor** (str) background color of the figure
- normed (bool) the colormap is rescaled every timestep when set to True, otherwise it
 is calculated from the global extrema
- **step** (*int*) the stepping between two timesteps
- deminc (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry

timeLongitude (*ifield=0*, *removeMean=True*, *lat0=0.0*, *levels=12*, *cm='RdYlBu_r'*, *deminc=True*) Plot the time-longitude diagram (input latitude can be chosen)

Parameters

- **ifield** (*int*) in case of a multiple-field movie file, you can change the default field displayed using the parameter ifield
- lat0 (float) value of the latitude
- levels (int) number of contour levels
- cm(str) name of the colormap
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry
- removeMean (bool) remove the time-averaged part when set to True

class magic.Movie3D (file=None, step=1, lastvar=None, nvar='all', nrout=48, ratio_out=2.0, potExtra=False, precision='Float32')

This class allows to read the 3D movie files $(B|V)_3D_-.TAG$ and transform them into a series of VTS files ./vtsFiles/B3D_#.TAG that can be further read using paraview.

```
>>> Movie3D(file='B_3D.TAG')
```

__init__ (file=None, step=1, lastvar=None, nvar='all', nrout=48, ratio_out=2.0, potExtra=False, precision='Float32')

Parameters

- **file** (str) file name
- nvar (int) the number of timesteps of the movie file we want to plot starting from the last line
- lastvar (int) the number of the last timestep to be read
- **step** (*int*) the stepping between two timesteps
- **precision** (*str*) precision of the input file, Float32 for single precision, Float64 for double precision
- potextra (bool) when set to True, potential extrapolation of the magnetic field outside the fluid domain is also computed
- ratio_out (float) ratio of desired external radius to the CMB radius. This is is only used when potExtra=True
- **nrout** (*int*) number of additional radial grid points to compute the potential extrapolation. This is only used when potExtra=True

9.3.9 Support for B_cmb_coeff.TAG and (V|B)_coeff_r#.TAG files

```
class magic.coeff.MagicCoeffCmb (tag=None, datadir='.', ratio\_cmb\_surface=1, scale\_b=1, iplot=True, lCut=None, precision='Float64', ave=False, sv=False, quiet=False)
```

This class allows to read the $B_coeff_cmb.TAG$ files. It first read the poloidal potential at the CMB and then transform it to the Gauss coefficients $g_{\ell m}$ and $h_{\ell m}$ using the getGauss function.

add (new)

Built-in function to sum two cmb files

Note: So far this function only works for two cmb files with the same grid sizes. At some point, we might introduce grid extrapolation to allow any summation/

```
__init__ (tag=None, datadir='.', ratio_cmb_surface=1, scale_b=1, iplot=True, lCut=None, precision='Float64', ave=False, sv=False, quiet=False)

A class to read the B_coeff_cmb files
```

- tag(str) if you specify a pattern, it tries to read the corresponding files
- ratio_cmb_surface (float) ratio of surface ratio to CMB radius (default is 1)
- scale_b (float) magnetic field unit (default is 1)
- iplot (int) a logical to toggle the plot (default is True)
- precision (char) single or double precision
- ave (bool) load a time-averaged CMB file when set to True
- sv (bool) load a dt_b CMB file when set to True
- quiet (bool) verbose when toggled to True (default is True)
- **1Cut** (*int*) reduce the spherical harmonic truncation to l <= 1Cut
- datadir (str) working directory

movieCmb (cut=0.5, levels=12, cm='RdYlBu_r', png=False, step=1, normed=False, dpi=80, bg-color=None, deminc=True, removeMean=False, precision='Float64', contour=False, mer=False)

Plotting function (it can also write the png files)

Parameters

- **levels** (*int*) number of contour levels
- cm(str) name of the colormap
- cut (float) adjust the contour extrema to max(abs(data))*cut
- png (bool) save the movie as a series of png files when set to True
- **dpi** (*int*) dot per inch when saving PNGs
- **bgcolor** (str) background color of the figure
- **normed** (bool) the colormap is rescaled every timestep when set to True, otherwise it is calculated from the global extrema
- **step** (*int*) the stepping between two timesteps
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry
- precision (char) single or double precision
- contour (bool) also display the solid contour levels when set to True
- mer (bool) display meridians and circles when set to True
- **removeMean** (bool) remove the time-averaged part when set to True

plot()

Display some results when iplot is set to True

timeLongitude (removeMean=True, lat0=0.0, levels=12, cm='RdYlBu_r', deminc=True, shtns_lib='shtns')

Plot the time-longitude diagram of Br (input latitude can be chosen)

Warning: the python bindings of SHTns are mandatory to use this plotting function!

- lat0 (float) value of the latitude
- **levels** (*int*) number of contour levels
- cm(str) name of the colormap
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry
- **shtns_lib** (char) version of shtns library used: can be either 'shtns' or 'shtns-magic'
- removeMean (bool) remove the time-averaged part when set to True

truncate (lCut)

Parameters 1Cut (*int*) – truncate to spherical harmonic degree lCut

precision='Float64', ICut=None, quiet=False)
This class allows to read the $B_coeff_r\#.TAG$ and $V_coeff_r\#.TAG$ files. It reads the poloidal and toroidal potentials and reconstruct the time series (or the energy) contained in any given mode.

```
>>> # Reads the files V_coeff_r2.test*
>>> cr = MagicCoeffR(tag='test*', field='V', r=2)
>>> print(cr.ell, cr.wlm) # print \ell and w_{\ell m}
>>> # Time-evolution of the poloidal energy in the (\ell=10, m=10) mode
>>> plot(cr.time, cr.epolLM[:, cr.idx[10, 10]])
```

__init__ (tag, ratio_cmb_surface=1, scale_b=1, iplot=True, field='B', r=1, precision='Float64', lCut=None, quiet=False)

Parameters

- tag(str) if you specify a pattern, it tries to read the corresponding files
- ratio_cmb_surface (float) ratio of surface ratio to CMB radius (default is 1)
- scale_b (float) magnetic field unit (default is 1)
- iplot (bool) a logical to toggle the plot (default is True)
- **field** (str) 'B', 'V' or 'T' (magnetic field, velocity field or temperature)
- **r** (*int*) an integer to characterise which file we want to plot
- **precision** (str) single or double precision
- **1Cut** (*int*) reduce the spherical harmonic truncation to l <= lCut
- quiet (bool) verbose when toggled to True (default is True)

fft()

Fourier transform of the poloidal energy

movieRad (cut=0.5, levels=12, cm='RdYlBu_r', png=False, step=1, normed=False, dpi=80, bg-color=None, deminc=True, removeMean=False, precision='Float64', contour=False, mer=False)

Plotting function (it can also write the png files)

Warning: the python bindings of SHTns are mandatory to use this plotting function!

- **levels** (*int*) number of contour levels
- cm(str) name of the colormap
- cut (float) adjust the contour extrema to max(abs(data))*cut
- png (bool) save the movie as a series of png files when set to True
- **dpi** (int) dot per inch when saving PNGs
- **bgcolor** (str) background color of the figure
- **normed** (bool) the colormap is rescaled every timestep when set to True, otherwise it is calculated from the global extrema
- **step** (*int*) the stepping between two timesteps
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry
- precision (char) single or double precision
- **contour** (bool) also display the solid contour levels when set to True
- mer (bool) display meridians and circles when set to True
- removeMean (bool) remove the time-averaged part when set to True

truncate (lCut, field='B')

Parameters

- 1Cut (int) truncate to spherical harmonic degree lCut
- **field** (char) name of the field ('V', 'B' or 'T')

magic.coeff.deriv(x, y, axis=0)

This function is a simple second order derivative

Parameters

- x (numpy.ndarray) input x-axis
- y (numpy.ndarray) input array

Returns an array that contains the derivatives

Return type numpy.ndarray

magic.coeff.getGauss(alm, blm, ell, m, scale_b, ratio_cmb_surface, rcmb)

Get the Gauss coefficients from the real and imaginary parts of the poloidal potential

Parameters

- alm (numpy.ndarray) real part of the poloidal potential
- blm (numpy.ndarray) imaginary part of the poloidal potential
- ell (numpy.ndarray) spherical harmonic degree ell
- scale_b (float) magnetic field unit (default is 1)
- ratio_cmb_surface (float) ratio of surface ratio to CMB radius (default is 1)
- rcmb (float) radius of the outer boundary

magic.coeff.rearangeLat (field)

This function is used to unfold the colatitudes

Parameters field (numpy.ndarray) – input array with MagIC ordering of colatitudes (i.e. successively Northern Hemisphere and Southern Hemisphere)

Returns an array with the regular ordering of the colatitudes

Return type numpy.ndarray

9.3.10 Support for B[rp]Spec.TAG

```
class magic.MagicRSpec (tag, field='Br', precision='Float32', avg=False)
```

This class allows to read the rB[r|p]Spec.TAG files. Those files contain the time-evolution of the poloidal/toroidal magnetic energy for all radii and for spherical harmonic degrees from 1 to 6. This is an unformatted fortran file.

```
>>> # Read all the `BrSpec.test*` files in the current working directory and
>>> # stack them.
>>> rsp = MagicRSpec(tag='test*', field='Br')
```

```
__init__ (tag, field='Br', precision='Float32', avg=False)
```

Parameters

- tag (str) if you specify a pattern, it tries to read the corresponding files and stack them.
- **field** (str) nature of the radial spectra. Possible choices are 'Bt' or 'Bp'
- **precision** (str) single or double precision (default single, i.e. 'Float32')
- avg (bool) when set to True, display time averaged quantities

plotAvg()

Plotting function for time-averaged profiles

9.3.11 Support for [V|B|T] lmr #.TAG

```
class magic.MagicPotential (field='V', datadir='.', tag=None, ave=False, ipot=None, preci-
sion='Float32')
```

This class allows to load and display the content of the potential files: $V_{lmr.TAG}$, $B_{lmr.TAG}$ and $T_{lmr.TAG}$. This class allows to transform the poloidal/toroidal potential in spectral space to the physical quantities in the physical space. It allows to plot radial and equatorial cuts as well as phi-averages.

```
>>> # To read T_lmr.test
>>> p = MagicPotential(field='T', ipot=1, tag='test')
>>> # To read the latest V_lmr file in the working directory
>>> p = MagicPotential(field='V')
>>> # Get the poloidal potential (lm, nR)
>>> wlm = p.pol
>>> # Obtain the value of w(l=12, m=12, nR=33)
>>> print( p.pol[p.idx[12,12], 32] )
```

```
>>> # Possible plots
>>> p.equat(field='vr')
>>> p.avg(field='vp')
>>> p.surf(field='vt', r=0.8)
```

__init__ (field='V', datadir='.', tag=None, ave=False, ipot=None, precision='Float32')

- **field** (str) 'B', 'V' or 'T' (magnetic field, velocity field or temperature)
- datadir (str) the working directory
- tag(str) if you specify a pattern, it tries to read the corresponding files
- ave (bool) plot a time-averaged spectrum when set to True
- ipot (int) the number of the lmr file you want to plot
- **precision** (str) single or double precision

Plot the azimutal average of a given field.

```
>>> p = MagicPotential(field='V')
>>> # Axisymmetric zonal flows, 65 contour levels
>>> p.avg(field='vp', levels=65, cm='seismic')
```

```
>>> # Minimal plot (no cbar, not title)
>>> p.avg(field='vr', tit=False, cbar=False)
```

Parameters

- **field** (str) the field you want to display
- **levels** (*int*) the number of levels in the contourf plot
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu_r', etc.)
- tit (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

equat (field='vr', levels=65, cm=u'seismic', normed=True, vmax=None, vmin=None, cbar=True, tit=True, normRad=False)
Plot the equatorial cut of a given field

```
>>> p = MagicPotential(field='B')
>>> # Equatorial cut of the Br
>>> p.equat(field='Br')
```

```
>>> # Normalise the contour levels radius by radius
>>> p.equat(field='Bphi', normRad=True)
```

- **field** (str) the name of the input physical quantity you want to display
- normRad (bool) when set to True, the contour levels are normalised radius by radius (default is False)
- **levels** (*int*) the number of levels in the contour

- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu_r', etc.)
- tit (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

```
>>> p = MagicPotential(field='V')
>>> # Radial flow component at ``r=0.95 r_o``, 65 contour levels
>>> p.surf(field='vr', r=0.95, levels=65, cm='seismic')
```

```
>>> # Control the limit of the colormap from -1e3 to 1e3
>>> p.surf(field='vp', r=1., vmin=-1e3, vmax=1e3, levels=33)
```

Parameters

- **field** (str) the name of the field you want to display
- **proj** (str) the type of projection. Default is Hammer, in case you want to use 'ortho' or 'moll', then Basemap is required.
- **lon_0** (*float*) central azimuth (only used with Basemap)
- lat_0 (float) central latitude (only used with Basemap)
- **r** (float) the radius at which you want to display the input data (in normalised units with the radius of the outer boundary)
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu_r', etc.)
- **tit** (bool) display the title of the figure when set to True
- cbar(bool) display the colorbar when set to True
- **lines** (bool) when set to True, over-plot solid lines to highlight the limits between two adjacent contour levels
- **vmax** (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero.

9.3.12 Support for TO outputs

```
class magic.TOMovie (file=None, iplot=True, cm='RdYlBu_r', cut=0.8, levels=16, avg=True, precision='Float32')
```

This class allows to read and display the $TO_mov.TAG$ generated when $l_TOmovie=.true$. is True.

```
>>> # This will allow you to pick up one TO_mov files among the existing ones
>>> t = TOMovie()
```

```
>>> # Read TO_mov.NOm2, time-averaged it and display it with 65 contour levels
>>> t = TOMovie(file='TO_mov.NOm2', avg=True, levels=65, cm='seismic')
```

__init__(file=None, iplot=True, cm='RdYlBu_r', cut=0.8, levels=16, avg=True, precision='Float32')

Parameters

- **file** (str) the filename of the TO_mov file
- cmap (str) the name of the color map
- **levels** (*int*) the number of contour levels
- cut (float) adjust the contour extrema to max(abs(data))*cut
- iplot (bool) a boolean to specify if one wants to plot or not the results
- avg(bool) time average of the different forces
- **precision** (*str*) precision of the input file, Float32 for single precision, Float64 for double precision

plot (cut=0.8, levs=16, avg=True, cmap='RdYlBu_r')
Plotting function

Parameters

- cut (float) adjust the contour extrema to max(abs(data))*cut
- **levs** (*int*) number of contour levels
- avg (bool) when set to True, quantities are time-averaged
- **cmap** (str) name of the colormap

class magic.**MagicTOZ** (*datadir='.'*, *itoz=None*, *tag=None*, *precision='Float32'*, *ave=False*)

This class can be used to read the TOZ.TAG files produced by the TO outputs

```
>>> # read the content of TOZ_1.tag
>>> # where tag is the most recent file in the current directory
>>> toz = MagicTOZ(itoz=1)
>>> # read the content of TOZ_ave.test
>>> toz = MagicTOZ(tag='test', ave=True)
```

__init__ (datadir='.', itoz=None, tag=None, precision='Float32', ave=False)

- datadir (str) current working directory
- tag (str) file suffix (tag), if not specified the most recent one in the current directory is chosen
- **precision** (str) single or double precision
- iplot (bool) display the output plot when set to True (default is True)
- **ave** (bool) plot a time-averaged TOZ file when set to True
- itoz (int) the number of the TOZ file you want to plot

class magic.MagicTOHemi (datadir='.', hemi='n', tag=None, precision='Float32', iplot=False)

This class can be used to read and display z-integrated quantities produced by the TO outputs. Those are basically the TO[sln]hn.TAG files

```
>>> to = MagicTOHemi(hemi='n', iplot=True) # For the Northern hemisphere
```

__init__ (datadir='.', hemi='n', tag=None, precision='Float32', iplot=False)

Parameters

- datadir (str) current working directory
- hemi (str) Northern or Southern hemisphere ('n' or 's')
- tag (str) file suffix (tag), if not specified the most recent one in the current directory is chosen
- precision (str) single or double precision
- **iplot** (bool) display the output plot when set to True (default is True)

plot()

Plotting function

class magic.MagicTaySphere (datadir='.', tag=None, precision='Float32', iplot=False)

This class can be used to read and display quantities produced by the TO outputs. Those are basically the TaySphere.TAG files

```
>>> to = MagicTaySphere(iplot=True) # For the Northern hemisphere
>>> print(to.time, to.e_kin)
```

__init__ (datadir='.', tag=None, precision='Float32', iplot=False)

Parameters

- datadir (str) current working directory
- tag (str) file suffix (tag), if not specified the most recent one in the current directory is chosen
- **precision** (str) single or double precision
- iplot (bool) display the output plot when set to True (default is True)

plot()

Plotting function

class magic.MagicPV (field='PVZ', datadir='.', tag=None, precision='Float32', iplot=False)

This class can be used to read and display quantities produced by the PV outputs. Those are basically the PVZ.TAG and the Vcy.TAG files

```
>>> # To plot the content of PVZ.test
>>> pv = MagicPV(field='PVZ', tag='test', iplot=True)
```

__init__ (field='PVZ', datadir='.', tag=None, precision='Float32', iplot=False)

- **field** (*str*) file prefix (either 'Vcy' or 'PVZ')
- datadir (str) current working directory
- tag (str) file suffix (tag), if not specified the most recent one in the current directory is chosen

- **precision** (str) single or double precision
- **iplot** (bool) display the output plot when set to True (default is True)

plot (*field*)
Plotting routine

Parameters field (str) – file prefix (either 'Vcy' or 'PVZ')

9.3.13 Run comparison

```
class magic.CompSims (file='liste', field='ts', ncol=4, cm='RdYlBu_r', dpi=96, normed=True, lev-
els=16, type=None, r=0.9, bw=False, ave=False, cut=1)
```

This class allows to compare an analyse several DNS simultaneously. It is possible to compare time-series or *graphic files*. To set it up, you first need to create a file that contains the list of directories you want to analyse:

```
$ cat inputList
E3e4Eps5e3Q05
E3e4Eps2e3Q07
E3e4Eps2e3Q08
E3e4Eps2e3Q09
```

This list thus contains four directories (one run per directory) that can be further analysed:

```
>>> # Display the time-series of kinetic energy on 2 columns
>>> CompSims(file='inputList', field='ts', ncol=2)
>>> # Display the equatorial cuts of v_r
>>> CompSims(file='inputList', field='vr', type='equat', levels=65, cm='seismic')
>>> # Display the radial cuts of B_r at r=0.8 r_o
>>> CompSims(file='inputList', field='br', type='surf', r=0.8)
>>> # Display the average zonal flow
>>> CompSims(file='inputList', field='vp', type='avg')
```

__init__ (file='liste', field='ts', ncol=4, cm='RdYlBu_r', dpi=96, normed=True, levels=16, type=None, r=0.9, bw=False, ave=False, cut=1)

- **file** (str) the input file that contains the list of directories that one wants to analyse
- **field** (str) name of the input field. Possible options are: 'ts': displaye the time-series of kinetic energy; 'e_mag': display the time-series of magnetic energy; 'flux': display the time-series of the Nusselt numbers; 'zonal': display the surface zonal flow; 'Anything else': try to interpret the field
- **type** (str) nature of the plot. Possible values are: 'avg' or 'slice': phi-average or phi-slice; 'equat': equatorial cut; 'surf': radial cut; 'ts*: time series
- ncol (int) number of columns of the figure
- ave (bool) when set to True, it tries to read a time-averaged graphic file
- **r** (*float*) the radius at which you want to display the input data (in normalised units with the radius of the outer boundary)
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu_r', etc.)
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

```
    dpi (int) - dot per inch when saving PNGs
    bw (bool) - when set to True, display grey-scaled contour levels
    cut (float) - adjust the contour extrema to max(abs(data))*cut
    plotAvg()
        Plot azimutal averages in (theta, r) planes.
    plotEmag()
        Plot time-series of the magnetic energy
    plotEquat()
        Plot equatorial cuts in (phi, r) planes.
    plotFlux()
        Plot time-series of the top and bottom Nusselt numbers
    plotSurf()
        Plot radial cuts in (phi, theta) planes using the Hammer projection.
    plotTs()
        Plot time-series of the kinetic energy
```

9.3.14 Conversion of G_#.TAG files to vts/vti files

Plot surface zonal flow profiles.

plotZonal()

This class allows to transform an input graphic file to a file format readable by paraview/visit or mayavi. It also allows to compute a possible potential extrapolation of the field lines in an arbitrary outer spherical shell domain

```
>>> # Load a graphic file
>>> gr = MagicGraph(ivar=1)
>>> # store myOut.vts
>>> Graph2Vtk(gr, 'myOut', outType='vts')
>>> # store u' and B for the vector fields and vortz and T for the scalars
>>> Graph2Vtk(gr, scals=['temp', 'vortz'], vecs=['ufluct', 'B'])
>>> # store only T'
>>> Graph2Vtk(gr, scals=['tempfluct'], vecs=[])
>>> # store only B with its potential extrapolation up to 3*r_cmb
>>> Graph2Vtk(gr, scals=[], vecs=['B'], potExtra=True, ratio_out=3)
>>> # Extrapolate on a cartesian grid of size 128^3
>>> Graph2Vtk(gr, outType='vti', nx=128, ny=128, nz=128)
```

```
__init__(gr, filename='out', scals=['vr', 'emag', 'tfluct'], vecs=['u', 'B'], potExtra=False, ratio_out=2, nrout=32, deminc=True, outType='vts', nFiles=1, nx=96, ny=96, nz=96, labFrame=False)
```

- **filename** (str) the file name of the output (without extension)
- qr (magic.MagicGraph) the input graphic file one wants to transform to vts/vti
- **scals** (list(str)) a list that contains the possible input scalars: 'entropy', 'vr', 'vp', 'tfluct', 'vortz', 'vortzfluct', 'ekin', 'emag', 'vortr', 'colat'

- **vecs** (list(str)) a list that contains the possible input vectors: 'u', 'b', 'ufluct', 'bfluct'
- **potExtra** (bool) when set to True, calculates the potential extrapolation of the magnetic field up to ratio_out*r_cmb
- ratio_out (float) in case of potential extrapolation, this is the ratio of the external outer radius to r cmb (rout/rcmb)
- **nrout** (*integer*) in case of potential extrapolation, this input allows to specify thenumber of radial grid points in the outer spherical envelope
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry
- **outType** (str) nature of the VTK file produced. This can be either 'vts' for the spherical grid or 'vti' for an extrapolation on a cartesian grid
- **nFiles** (*int*) number of output chunks in case of parallel vts file format (pvts)
- $\mathbf{nx}(int)$ number of grid points in the x direction
- **ny** (*int*) number of grid points in the x direction
- nz (int) number of grid points in the x direction
- labFrame (bool) when set to True, transform the velocity to the lab frame

writeVTI (*filename*, *nx*=96, *ny*=96, *nz*=96)

In this case, the output is extrapolated on a cartesian grid and then written in a vti file.

Parameters

- **filename** (str) the file name of the output (without extension)
- $\mathbf{nx}(int)$ number of grid points in the x direction
- **ny** (*int*) number of grid points in the x direction
- nz (int) number of grid points in the x direction

writeVTS (filename, nFiles)

This function stores the output on a structured-grid vts file.

Parameters

- **filename** (str) the file name of the output (without extension)
- **nFiles** (*int*) number of outpute files (in case of pvts)

magic.graph2vtk.sph2cart scal(scals, radius, nx=96, ny=96, ny=96, minc=1)

This function interpolates a series of scalar fields from the spherical coordinates to the cartesian coordinates.

- scals (numpy.ndarray[nscals,nphi,ntheta,nr]) an array that contains the different scalar quantities
- radius (numpy.ndarray) the input radius
- **nx** (int) number of grid points in the x direction
- **ny** (*int*) number of grid points in the x direction
- **nz** (*int*) number of grid points in the x direction
- minc (int) azimuthal symmetry

Returns a tuple that contains the scalars, the max of the grid and the grid spacing

Return type (numpy.ndarray[nscals,nz,ny,nx],float,float)

magic.graph2vtk.sph2cart_vec (vecr, vect, vecp, radius, nx=96, ny=96, nz=96, minc=1)

This function interpolates a series of vector fields from the spherical coordinates to the cartesian coordinates.

Parameters

- **vecr**(numpy.ndarray[nvecs,nphi,ntheta,nr])—the radial components of the different vector fields
- **vect** (numpy.ndarray[nvecs,nphi,ntheta,nr]) the latitudinal components of the different vector fields
- vecp (numpy.ndarray[nvecs, nphi, ntheta, nr]) the azimuthal components of the different vector fields
- radius (numpy.ndarray) the input radius
- **nx** (*int*) number of grid points in the x direction
- **ny** (int) number of grid points in the x direction
- nz (int) number of grid points in the x direction
- minc (int) azimuthal symmetry

Returns a tuple that contains the three vectors components

Return type (numpy.ndarray[nvecs,nz,ny,nx],..)

9.3.15 Potential extrapolation

This class is used to compute the potential field extrapolation of the magnetic field in an arbitrary outer spherical shell domain. It takes as an input the magnetic field at the CMB.

init (rcmb, brcmb, minc, ratio out=2.0, nrout=32, cutCMB=False, deminc=True)

Parameters

- bcmb (numpy.ndarary) the surface radial field, array of dimension [np, nt]
- rcmb (float) the value of the radius at the surface
- minc (int) azimuthal symmetry
- ratio_out (float) the ratio of the outer sphere radius to the surface radius
- **nrout** (*int*) the number of radial point (linearly spaced) of the extrapolated field in the outer spherical domain
- **cutCMB** (bool) a logical if one wants to remove the first grid point (useful if one then wants to merge the graphic file with the extrapolation)
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry

 $\verb"avg" (field='br', levels=12, cm='RdYlBu_r', normed=True, vmax=None, vmin=None)"$

A small routine to plot the azimuthal averages of the extrapolated fields.

Parameters

• **field** (str) – the quantity you want to plot: 'br' or 'bp'

- **levels** (*int*) the number of contour levels
- cm(str) the name of the colormap
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

9.3.16 Additional possible analyses

class magic.bLayers.BLayers(iplot=False, quiet=False)

This class allows to determine the viscous and thermal boundary layers using several classical methods (slope method, peak values, dissipation rates, etc.). It uses the following files:

- Kinetic energy: eKinR.TAG
- Power budget: powerR.TAG
- Radial profiles used for boundary layers: bLayersR.TAG

This function can thus **only** be used when both *powerR.TAG* and *bLayersR.TAG* exist in the working directory.

Warning: This function works well as long as rigid boundaries and fixed temperature boundary conditions are employed. Other combination of boundary conditions (fixed fluxes and/or stress-free) might give wrong results, since boundary layers become awkward to define in that case.

Since this function is supposed to use time-averaged quantities, the usual procedure is first to define the initial averaging time using <code>AvgField</code>: (this needs to be done only once)

```
>>> a = AvgField(tstart=2.58)
```

Once the tInitAvg file exists, the boundary layer calculation can be done:

```
>>> bl = BLayers(iplot=True)
>>> # print the formatted output
>>> print(bl)
```

__init__(iplot=False, quiet=False)

Parameters

- **iplot** (bool) display the result when set to True (default False)
- quiet (bool) less verbose when set to True (default is False)

```
__str__()
```

Formatted output

plot()

Plotting function

```
magic.bLayers.getAccuratePeaks(rad, uh, uhTop, uhBot, ri, ro)
```

This functions performs a spline extrapolation around the maxima of the input array uh to define a more accurate location of the boundary layer.

- rad (numpy.ndarray) radius
- **uh** (numpy.ndarray) the horizontal velocity profile
- **uhTop** (float) first peak value of uh close to the outer boundary
- **uhBot** (float) first peak value of uh close to the inner boundary
- ri (float) the inner core radius
- ro (float) the outer core radius

Returns four floats: thickness of the bottom boundary layer, thickness of the top boundary layer, extrapolated value of uh at the bottom boundary layer, extrapolated value of uh at the top boundary layer

Return type list

magic.bLayers.getMaxima(field)

This function determines the local maxima of the input array field

Parameters field (numpy.ndarray) – the input array

Returns a list containing the indices of the local maxima

Return type list

magic.bLayers.integBotTop(rad, field, ri, ro, lambdai, lambdao, normed=False)

This function evaluates the radial integral of the input array field in the bottom and top boundary layers separately.

Parameters

- rad (numpy.ndarray) radius
- field (numpy.ndarray) the input radial profile
- ri (float) the inner core radius
- ro (float) the outer core radius
- lambdai (float) thickness of the inner boundary layer
- lambdao (float) thickness of the outer boundary layer
- **normed** (bool) when set to True, the outputs are normalised by the volumes of the boundary layers. In that case, the outputs are volume-averaged quantities.

Returns two floats that contains the bottom and top boundary layers integrations (integBot, integTop)

Return type list

magic.bLayers.integBulkBc(rad, field, ri, ro, lambdai, lambdao, normed=False)

This function evaluates the radial integral of the input array field in the boundary layer and in the bulk separately.

- rad (numpy.ndarray) radius
- **field** (numpy.ndarray) the input radial profile
- ri (float) the inner core radius
- ro (float) the outer core radius
- lambdai (float) thickness of the inner boundary layer
- lambdao (float) thickness of the outer boundary layer

• **normed** (bool) – when set to True, the outputs are normalised by the volumes of the boundary layers and the fluid bulk, respectively. In that case, the outputs are volume-averaged quantities.

Returns two floats that contains the boundary layer and the bulk integrations (integBc, integBulk)

Return type list

```
class magic.ThetaHeat (iplot=False, angle=10, pickleName='thHeat.pickle')
```

This class allows to conduct some analysis of the latitudinal variation of the heat transfer. It relies on the movie files *ATmov.TAG* and *AHF_mov.TAG*. As it's a bit time-consuming, the calculations are stored in a python.pickle file to quicken future usage of the data.

This function can **only** be used when *bLayersR.TAG* exist in the working directory.

Since this function is supposed to use time-averaged quantities, the usual procedure is first to define the initial averaging time using AvgField: (this needs to be done only once)

```
>>> a = AvgField(tstart=2.58)
```

Once the tInitAvq file exists, the latitudinal heat transfer analysis can be done using:

```
>>> # For chunk-averages over 10^\degree in the polar and equatorial regions.
>>> th = ThetaHeat(angle=10)
>>> # Formatted output
>>> print(th)
```

__init__ (iplot=False, angle=10, pickleName='thHeat.pickle')

Parameters

- **iplot** (bool) a boolean to toggle the plots on/off
- **angle** (float) the integration angle in degrees

PickleName calculations a

```
__str___()
```

Formatted outputs

```
>>> th = ThetaHeat()
>>> print(th)
```

plot()

Plotting function

```
class magic.cyl.Cyl(ivar=1, datadir='.', ns=None)
```

This class allows to extrapolate a given *graphic file* on a cylindrical grid. Once done, the extrapolated file is stored in a python.pickle file. It is then possible to display 2-D cuts of the extrapolated arrays (radial cuts, phi-averages, equatorial cuts, z-averages and phi-slices)

Warning: This process is actually **very demanding** and it might take a lot of time to extrapolate the G_#.TAG file. Be careful when choosing the input value of ns!

```
>>> # Extrapolate the G file to the cylindrical grid (ns=128, nz=2*ns)
>>> c = Cyl(ivar=1, ns=128)
>>> # Radial cut of v_r
>>> c.surf(field='vr', r=0.8)
>>> # Vertical average of B_\phi
```

```
>>> c.avgz(field='Bphi', cm='seismic', levels=33)
>>> # Azimuthal average of v_\phi
>>> c.avg(field='Bphi')
>>> # Equatorial cut of of v_theta
>>> c.equat(field='vtheta')
```

```
___init__(ivar=1, datadir='.', ns=None)
```

- ivar (int) the number of the Graphic file
- datadir (str) working directory
- **ns** (*int*) number of grid points in the radial direction

avg (field='Bphi', levels=16, cm='RdYlBu_r', normed=True, vmax=None, vmin=None)
Plot the azimutal average of a given field.

```
>>> c = Cyl(ns=65)
>>> # Azimuthal average of B_r
>>> c.avg(field='Br', cm='seismic', levels=33)
```

Parameters

- **field** (str) name of the input field
- levels (int) number of contour levels
- cm(str) name of the color map
- **normed** (bool) when set to True, the contours are normalised fro -max(field), max(field)
- **vmin** (float) truncate the contour levels to values > vmin
- **vmax** (float) truncate the contour levels to values < vmax

avgz (field='vs', levels=16, cm='RdYlBu_r', normed=True, vmin=None, vmax=None, avg=False) Plot the vertical average of a given field.

```
>>> c = Cyl(ns=65)
>>> # Vertical average of v_s
>>> c.avg(field='vs', cm='seismic', levels=33)
```

- **field** (str) name of the input field
- **levels** (*int*) number of contour levels
- $\mathbf{cm}(str)$ name of the color map
- normed (bool) when set to True, the contours are normalised fro -max(field), max(field)
- **vmin** (float) truncate the contour levels to values > vmin
- **vmax** (float) truncate the contour levels to values < vmax
- avg (bool) when set to True, an additional figure with the phi-average profile is also displayed

equat (field='vs', levels=16, cm='RdYlBu_r', normed=True, vmax=None, vmin=None)
Plot an input field in the equatorial plane.

```
>>> c = Cyl(ns=65)
>>> # Equatorial cut of v_\phi
>>> c.equat(field='vphi', cm='seismic', levels=33)
```

Parameters

- **field** (str) name of the input field
- levels (int) number of contour levels
- cm(str) name of the color map
- **normed** (bool) when set to True, the contours are normalised fro -max(field), max(field)
- **vmin** (float) truncate the contour levels to values > vmin
- **vmax** (float) truncate the contour levels to values < vmax

slice (*field='Bphi'*, *lon_0=0.0*, *levels=16*, *cm='RdYlBu_r'*, *normed=True*) Plot an azimuthal slice of a given field.

```
>>> c = Cyl(ns=65)
>>> # Slices of v_r at 30 and 60 degrees
>>> c.slice(field='vr', lon_0=[30, 60])
```

Parameters

- **field** (str) name of the input field
- lon_0 (float or list) the longitude of the slice in degrees, or a list of longitudes
- levels (int) number of contour levels
- $\mathbf{cm}(str)$ name of the color map
- normed (bool) when set to True, the contours are normalised fro -max(field), max(field)

surf (field='Bphi', r=0.85, vmin=None, vmax=None, levels=16, cm='RdYlBu_r', normed=True, figsize=None)

Plot the surface distribution of an input field at a given input radius (normalised by the outer boundary radius).

```
>>> c = Cyl(ns=65)
>>> # Surface plot of B_\phi from -10 to 10
>>> c.surf(field='Bphi', r=0.6, vmin=-10, vmax=10, levels=65)
```

- **field** (str) name of the input field
- **r** (*float*) radial level (normalised to the outer boundary radius)
- levels (int) number of contour levels
- cm(str) name of the color map

- **normed** (bool) when set to True, the contours are normalised fro -max(field), max(field)
- **vmin** (float) truncate the contour levels to values > vmin
- vmax (float) truncate the contour levels to values < vmax

```
magic.cyl.sph2cyl(g, ns=None, nz=None)
```

This function interpolates the three flow (or magnetic field) component of a $G_{\#}.TAG$ file on a cylindrical grid of size (ns, nz).

Warning: This might be really slow!

Parameters

- g (magic.MagicGraph) input graphic output file
- ns (int) number of grid points in the radial direction
- nz (int) number of grid points in the vertical direction

Returns a python tuple of five numpy.ndarray (S,Z,vs,vp_cyl,vz). S[nz,ns] is a meshgrid that contains the radial coordinate. Z[nz,ns] is a meshgrid that contains the vertical coordinate. vs[nz,ns] is the radial component of the velocity (or magnetic field), vp_cyl[nz,ns] the azimuthal component and vz[nz,ns] the vertical component.

Return type tuple

magic.cyl.sph2cyl_plane(data, rad, ns, nz)

This function extrapolates a phi-slice of a spherical shell on a cylindrical grid

```
>>> # Read G_1.test
>>> gr = MagicGraph(ivar=1, tag='test')
>>> # phi-average v_\phi and s
>>> vpm = gr.vphi.mean(axis=0)
>>> sm = gr.entropy.mean(axis=0)
>>> # Interpolate on a cylindrical grid
>>> Z, S, outputs = sph2cyl_plane([vpm, sm], gr.radius, 512, 1024)
>>> vpm_cyl, sm_cyl = outputs
```

Parameters

- data (list (numpy.ndarray)) a list of 2-D arrays [(ntheta, nr), (ntheta, nr), ...]
- rad (numpy.ndarray) radius
- **ns** (*int*) number of grid points in s direction
- **nz** (*int*) number of grid points in z direction

Returns a python tuple that contains two numpy.ndarray and a list (S,Z,output). S[nz,ns] is a meshgrid that contains the radial coordinate. Z[nz,ns] is a meshgrid that contains the vertical coordinate. output=[arr1[nz,ns], ..., arrN[nz,ns]] is a list of the interpolated array on the cylindrical grid.

Return type tuple

magic.cyl.zavg(input, radius, ns, minc, save=True, filename='vp.pickle', normed=True)

This function computes a z-integration of a list of input arrays (on the spherical grid). This works well for 2-D (phi-slice) arrays. In case of 3-D arrays, only one element is allowed (too demanding otherwise).

Parameters

- input (list (numpy.ndarray)) a list of 2-D or 3-D arrays
- radius (numpy.ndarray) spherical radius
- **ns** (int) radial resolution of the cylindrical grid (nz=2*ns)
- minc (int) azimuthal symmetry
- **save** (bool) a boolean to specify if one wants to save the outputs into a pickle (default is True)
- **filename** (str) name of the output pickle when save=True
- **normed** (bool) a boolean to specify if ones wants to simply integrate over z or compute a z-average (default is True: average)

Returns a python tuple that contains two numpy.ndarray and a list (height,cylRad,output) height[ns] is the height of the spherical shell for all radii. cylRad[ns] is the cylindrical radius. output=[arr1[ns], ..., arrN[ns]] contains the z-integrated output arrays.

Return type tuple

class magic.Butterfly (file=None, step=1, iplot=True, rad=0.8, lastvar=None, nvar='all', levels=20, cm='RdYlBu r', precision='Float32', cut=0.8)

This class can be used to display the time evolution of the magnetic field for various latitudes (i.e. the well-known butterfly diagrams). These diagrams are usually constructed using MagIC's *movie files*: either radial cuts (like Br_CMB_mov.TAG) or azimuthal-average (like AB_mov.TAG).

___add___(new)

Overload of the addition operator

```
>>> # Read 2 files
>>> b1 = Butterfly(file='AB_mov.test1', iplot=False)
>>> b2 = Butterfly(file='AB_mov.test2', iplot=False)
>>> # Stack them and display the whole thing
>>> b = b1+b2
>>> b.plot(levels=33, contour=True, cut=0.8, cm='seismic')
```

__init__(file=None, step=1, iplot=True, rad=0.8, lastvar=None, nvar='all', levels=20, cm='RdYlBu_r', precision='Float32', cut=0.8)

- **file** (str) when specified, the constructor reads this file, otherwise a list with the possible options is displayed
- rad (float) radial level (normalised to the outer boundary radius)
- iplot (bool) display/hide the plots (default is True)
- **nvar** (*int*) the number of time steps (lines) of the movie file we want to plot starting from the last line

- lastvar (int) the number of the last time step to be read
- **step** (*int*) the stepping between two lines
- levels (int) the number of contour levels
- cm(str) the name of the color map
- cut (float) adjust the contour extrema to max(abs(data))*cut
- precision (bool) precision of the input file, Float32 for single precision, Float64 for double precision

fourier2D (renorm=False)

This function allows to conduct some basic Fourier analysis on the data. It displays two figures: the first one is a contour levels in the (Frequency, Latitude) plane, the second one is integrated over latitudes (thus a simple, power vs Frequency plot)

```
>>> # Load the data without plotting
>>> b1 = Butterfly(file='AB_mov.test1', iplot=False)
>>> # Fourier analysis
>>> b1.fourier2D()
```

Parameters renorm (bool) – when set to True, it rebins the time series in case of irregularly spaced data

plot (levels=12, contour=False, renorm=False, cut=0.5, mesh=3, cm='RdYlBu_R')
Plotting function

Parameters

- cm(str) name of the colormap
- **levels** (*int*) the number of contour levels (only used when iplot=True and contour=True)
- **contour** (bool) when set to True, display contour levels (pylab.contourf), when set to False, display an image (pylab.imshow)
- renorm (bool) when set to True, it re-bins the time series in case of irregularly time-spaced data
- mesh (int) when renorm=True, factor of regriding: NewTime = mesh*OldTime
- cut (float) adjust the contour extrema to max(abs(data))*cut

9.3.17 Spectral tansforms

This python class is used to compute Legendre and Fourier transforms from spectral to physical space. It works in two steps: one first needs to initialize the transform

```
>>> sh = SpectralTransforms( 1_max=256, lm_max=33153, n_theta_max=384)
>>> print(Tlm[:, 10].shape) # lm_max (Temperature at ir=10)
>>> T = sh.spec_spat(Tlm) # T[n_phi_max, n_theta_max]
```

spat_spec(input)

This subroutine computes a transfrom from spatial representation (n_phi,n_theta) to spectral representation (lm_max). It returns one complex 1-D array (dimension(n_phi_max))

```
>>> gr = MagicGraph()
>>> sh = SpectralTransforms(gr.l_max, gr.minc, gr.lm_max, gr.n_theta_max)
>>> vr = gr.vr[:,:,30] # Radius ir=30
>>> vrlm = sh.spat_spec(vr) # vrlm is a complex array (lm_max)
>>> # Caculation of the poloidal potential from vr:
>>> wlm = np.zeros_like(vrlm)
>>> wlm[1:] = vrlm[1:]/(sh.ell[1:]*(sh.ell[1:]+1))*gr.radius[30]**2
```

Parameters input (numpy.ndarray) – input array in the physical space (n_phi,n_theta)

Returns output array in the spectral space (lm_max)

Return type numpy.ndarray

```
spec_spat (*args, **kwargs)
```

This subroutine computes a transfrom from spectral to spatial for all latitudes. It returns either one or two 2-D arrays (dimension(n_phi_max,n_theta_max)) depending if only the poloidal or both the poloidal and the toroidal potentials are given as input quantities.

```
>>> print(wlmr.shape) # lm_max
>>> vr = spec_spat_equat(wlmr)
>>> print(vr.shape) # n_phi, n_theta
>>> vt, vp = spec_spat_equat(dwdrlmr, zlmr)
```

spec spat dphi(polo)

This routine computes the phi-derivative and the transform from spectral to spatrial spaces. It returns a 2-D array of dimension (n_phi,n_theta)

```
>>> p = MagicPotential('V')
>>> vrlm = p.pol*p.ell*(p.ell+1)/p.radius[ir]**2/p.rho0[ir] # vr at r=ir
>>> dvrdp = p.sh.spec_spat_dphi(vrlm) # phi-derivative of vr
```

Parameters polo (numpy.ndarray) – the input array(lm_max) in spectral space

Returns the phi derivative in the physical space (n_phi, n_theta)

Return type numpy.ndarray

spec_spat_dtheta (polo, l_axi=False)

This routine computes the theta-derivative and the transform from spectral to spatrial spaces. It returns a 2-D array of dimension (n_phi,n_theta)

```
>>> p = MagicPotential('V')
>>> vrlm = p.pol*p.ell*(p.ell+1)/p.radius[ir]**2/p.rho0[ir] # vr at r=ir
>>> dvrdt = p.sh.spec_spat_dtheta(vrlm) # theta-derivative of vr
```

Parameters

- polo (numpy.ndarray) the input array(lm_max) in spectral space
- 1 axi (bool) switch to True, if only the axisymmetric field is needed

Returns the theta derivative in the physical space (n phi, n theta)

Return type numpy.ndarray

```
spec_spat_equat (*args)
```

This subroutine computes a transfrom from spectral to spatial at the equator. It returns either one or two 1-D arrays (dimension(n_phi_max)) depending if only the poloidal or both the poloidal and the toroidal potentials are given as input quantities.

```
>>> print(wlmr.shape) # lm_max
>>> vr = spec_spat_equat(wlmr)
>>> print(vr.shape) # n_phi
>>> vt, vp = spec_spat_equat(dwdrlmr, zlmr)
```

9.3.18 Plotting functions

magic.plotlib.cut(dat, vmax=None, vmin=None)

This functions truncates the values of an input array that are beyond vmax or below vmin and replace them by vmax and vmin, respectively.

```
>>> # Keep only values between -1e3 and 1e3
>>> datNew = cut(dat, vmin=-1e3, vmax=1e3)
```

Parameters

- dat (numpy.ndarray) an input array
- vmax (float) maximum upper bound
- vmin (float) minimum lower bound

Returns an array where the values >=vmax have been replaced by vmax and the values <=vmin have been replaced by vmin

Return type numpy.ndarray

Plot the equatorial cut of a given field

- data (numpy.ndarray) the input data (an array of size (nphi,nr))
- radius (numpy.ndarray) the input radius
- minc (int) azimuthal symmetry
- label (str) the name of the input physical quantity you want to display
- normRad (bool) when set to True, the contour levels are normalised radius by radius (default is False)
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu_r', etc.)
- **tit** (bool) display the title of the figure when set to True
- **cbar** (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- vmin (float) minimum value of the contour levels

- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry

magic.plotlib.hammer2cart (ttheta, pphi, colat=False)

This function is used to define the Hammer projection used when plotting surface contours in magic. Surf

```
>>> # Load Graphic file
>>> gr = MagicGraph()
>>> # Meshgrid
>>> pphi, ttheta = mgrid[-np.pi:np.pi:gr.nphi*1j, np.pi/2.:-np.pi/2.:gr.ntheta*1j]
>>> x,y = hammer2cart(ttheta, pphi)
>>> # Contour plots
>>> contourf(x, y, gr.vphi)
```

Parameters

- ttheta (numpy.ndarray) meshgrid [nphi, ntheta] for the latitudinal direction
- **pphi** meshgrid [nphi, ntheta] for the azimuthal direction
- **colat** (numpy.ndarray) colatitudes (when not specified a regular grid is assumed)

Returns a tuple that contains two [nphi, ntheta] arrays: the x, y meshgrid used in contour plots

Return type (numpy.ndarray, numpy.ndarray)

magic.plotlib.merContour(data, radius, label=None, levels=65, cm=u'seismic', normed=True, vmax=None, vmin=None, cbar=True, tit=True)

Plot a meridional cut of a given field

Parameters

- data (numpy.ndarray) the input data (an array of size (ntheta,nr))
- radius (numpy.ndarray) the input radius
- label (str) the name of the input physical quantity you want to display
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu_r', etc.)
- tit (bool) display the title of the figure when set to True
- **cbar** (bool) display the colorbar when set to True
- **vmax** (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

```
magic.plotlib.radialContour(data, rad=0.85, label=None, proj='hammer', lon_0=0.0, vmax=None, vmin=None, lat_0=30.0, levels=65, cm=u'seismic', normed=True, cbar=True, tit=True, lines=False)
```

Plot the radial cut of a given field

- data (numpy.ndarray) the input data (an array of size (nphi,ntheta))
- rad (float) the value of the selected radius

- label (str) the name of the input physical quantity you want to display
- **proj** (str) the type of projection. Default is Hammer, in case you want to use 'ortho' or 'moll', then Basemap is required.
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu_r', etc.)
- **tit** (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- **lines** (bool) when set to True, over-plot solid lines to highlight the limits between two adjacent contour levels
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

9.3.19 Various useful functions

magic.libmagic.anelprof (radius, strat, polind, g0=0.0, g1=0.0, g2=1.0)

This functions calculates the reference temperature and density profiles of an anelastic model.

```
>>> rad = chebgrid(65, 1.5, 2.5)
>>> temp, rho, beta = anelprof(rad, strat=5., polind=2.)
```

Parameters

- radius (numpy.ndarray) the radial gridpoints
- polind (float) the polytropic index
- **strat** (*float*) the number of the density scale heights between the inner and the outer boundary
- g0 (float) gravity profile: g=g0
- **g1** (float) gravity profile: g=g1*r/r_o
- **g2** (float) gravity profile: $g=g2*(r_o/r)**2$

Returns a tuple that contains the temperature profile, the density profile and the log-derivative of the density profile versus radius

Return type (numpy.ndarray, numpy.ndarray, numpy.ndarray)

```
magic.libmagic.avgField(time, field, tstart=None, std=False)
```

This subroutine computes the time-average (and the std) of a time series

```
>>> ts = MagicTs(field='misc', iplot=False, all=True)
>>> nuavg = avgField(ts.time, ts.topnuss, 0.35)
>>> print(nuavg)
```

Parameters

• time (numpy.ndarray) - time

- **field** (numpy.ndarray) the time series of a given field
- tstart (float) the starting time of the averaging
- std (bool) when set to True, the standard deviation is also calculated

Returns the time-averaged quantity

Return type float

```
magic.libmagic.chebgrid(nr, a, b)
```

This function defines a Gauss-Lobatto grid from a to b.

```
>>> r_icb = 0.5 ; r_cmb = 1.5; n_r_max=65
>>> rr = chebgrid(n_r_max, r_icb, r_cmb)
```

Parameters

- **nr** (*int*) number of radial grid points
- a (float) lower limit of the Gauss-Lobatto grid
- **b** (float) upper limit of the Gauss-Lobatto grid

Returns the Gauss-Lobatto grid

Return type numpy.ndarray

```
magic.libmagic.cylSder(radius, data, order=4)
```

This function computes the s derivative of an input array defined on a regularly-spaced cylindrical grid.

```
>>> s = linspace(0., 1., 129; dat = cos(s)
>>> ddatds = cylSder(s, dat)
```

Parameters

- radius (numpy.ndarray) cylindrical radius
- data (numpy.ndarray) input data
- **order** (*int*) order of the finite-difference scheme (possible values are 2 or 4)

Returns s derivative

Return type numpy.ndarray

```
magic.libmagic.cylZder(z, data)
```

This function computes the z derivative of an input array defined on a regularly-spaced cylindrical grid.

```
>>> z = linspace(-1., 1., 129; dat = cos(z)
>>> ddatdz = cylZder(z, dat)
```

Parameters

- z (numpy.ndarray) height of the cylinder
- data (numpy.ndarray) input data

Returns z derivative

Return type numpy.ndarray

magic.libmagic.fast_read(file, skiplines=0, binary=False, precision='Float64')

This function reads an input ascii table (can read both formatted or unformatted fortran)

```
>>> # Read 'e_kin.test', skip the first 10 lines
>>> data = fast_read('e_kin.test', skiplines=10)
```

Parameters

- **file** (str) name of the input file
- **skiplines** (*int*) number of header lines to be skept during reading
- **binary** (bool) when set to True, try to read an unformatted binray Fortran file (default is False)
- **precision** (str) single ('Float32') or double precision ('Float64')

Returns an array[nlines, ncols] that contains the data of the ascii file

Return type numpy.ndarray

```
magic.libmagic.getCpuTime (file)
```

This function calculates the CPU time from one given log file

Parameters file (file) – the log file you want to analyze

Returns the total CPU time

Return type float

```
magic.libmagic.getTotalRunTime()
```

This function calculates the total CPU time of one run directory

Returns the total RUN time

Return type float

```
magic.libmagic.intcheb (f, nr, z1, z2)
```

This function integrates an input function f defined on the Gauss-Lobatto grid.

```
>>> print(intcheb(f, 65, 0.5, 1.5))
```

Parameters

- **f** an input array
- **nr** (*int*) number of radial grid points
- **z1** (float) lower limit of the Gauss-Lobatto grid
- **z2** (float) upper limit of the Gauss-Lobatto grid

Type numpy.ndarray

Returns the integrated quantity

Return type float

```
magic.libmagic.matder (nr, z1, z2)
```

This function calculates the derivative in Chebyshev space.

```
>>> r_icb = 0.5 ; r_cmb = 1.5; n_r_max=65
>>> d1 = matder(n_r_max, r_icb, r_cmb)
>>> # Chebyshev grid and data
>>> rr = chebgrid(n_r_max, r_icb, r_cmb)
>>> f = sin(rr)
>>> # Radial derivative
>>> df = dot(d1, f)
```

- **nr** (*int*) number of radial grid points
- **z1** (float) lower limit of the Gauss-Lobatto grid
- **z2** (float) upper limit of the Gauss-Lobatto grid

Returns a matrix of dimension (nr,nr) to calculate the derivatives

Return type numpy.ndarray

magic.libmagic.phideravg (*data*, *minc=1*, *order=4*) phi-derivative of an input array

```
>>> gr = MagicGraph()
>>> dvphidp = phideravg(gr.vphi, minc=gr.minc)
```

Parameters

- data (numpy.ndarray) input array
- minc(int) azimuthal symmetry
- order (int) order of the finite-difference scheme (possible values are 2 or 4)

Returns the phi-derivative of the input array

Return type numpy.ndarray

magic.libmagic.progressbar(it, prefix=", size=60)

Fancy progress-bar for loops

```
for i in progressbar(range(1000000)):
    x = i
```

Parameters

- **prefix** (str) prefix string before progress bar
- size (int) width of the progress bar (in points of xterm width)

magic.libmagic.rderavg(data, eta=0.35, spectral=True, exclude=False)

Radial derivative of an input array

```
>>> gr = MagiGraph()
>>> dvrdr = rderavg(gr.vr, eta=gr.radratio)
```

Parameters

• data (numpy.ndarray) - input array

- eta (float) aspect ratio of the spherical shell
- **spectral** (bool) when set to True use Chebyshev derivatives, otherwise use finite differences (default is True)
- **exclude** (bool) when set to True, exclude the first and last radial grid points and replace them by a spline extrapolation (default is False)

Returns the radial derivative of the input array

Return type numpy.ndarray

magic.libmagic.scanDir(pattern, tfix=None)

This function sorts the files which match a given input pattern from the oldest to the most recent one (in the current working directory)

```
>>> dat = scanDir('log.*')
>>> print(log)
```

Parameters

- pattern (str) a classical regexp pattern
- **tfix** (float) in case you want to add only the files that are more recent than a certain date, use tfix (computer 1970 format!!)

Returns a list of files that match the input pattern

Return type list

magic.libmagic.sderavg(data, eta=0.35, spectral=True, colat=None, exclude=False) s derivative of an input array

```
>>> gr = MagiGraph()
>>> dvpds = sderavg(gr.vphi, eta=gr.radratio, colat=gr.colatitude)
```

Parameters

- data (numpy.ndarray) input array
- eta (float) aspect ratio of the spherical shell
- **spectral** (bool) when set to True use Chebyshev derivatives, otherwise use finite differences (default is True)
- **exclude** (bool) when set to True, exclude the first and last radial grid points and replace them by a spline extrapolation (default is False)
- colat (numpy.ndarray) colatitudes (when not specified a regular grid is assumed)

Returns the s derivative of the input array

Return type numpy.ndarray

```
magic.libmagic.selectField(obj, field, labTex=True)
```

This function selects for you which field you want to display. It actually allows to avoid possible variables miss-spelling: i.e. 'Bphi'='bp'='Bp'='bphi'

Parameters

- obj (magic.MagicGraph) a graphic output file
- **field** (str) the name of the field one wants to select

• labTex (bool) – when set to True, format the labels using LaTeX fonts

Returns a tuple that contains the selected physical field and its label

Return type (numpy.ndarray, str)

magic.libmagic.symmetrize(data, ms, reversed=False)

Symmetrise an array which is defined only with an azimuthal symmetry minc=ms

Parameters

- data (numpy.ndarray) the input array
- ms (int) the azimuthal symmetry
- reversed (bool) set to True, in case the array is reversed (i.e. n_phi is the last column)

Returns an output array of dimension (data.shape[0]*ms+1)

Return type numpy.ndarray

magic.libmagic.thetaderavg(data, order=4)

Theta-derivative of an input array (finite differences)

```
>>> gr = MagiGraph()
>>> dvtdt = thetaderavg(gr.vtheta)
```

Parameters

- data (numpy.ndarray) input array
- order (int) order of the finite-difference scheme (possible values are 2 or 4)

Returns the theta-derivative of the input array

Return type numpy.ndarray

magic.libmagic.writeVpEq(par, tstart)

This function computes the time-averaged surface zonal flow (and Rolc) and format the output

```
>>> # Reads all the par.* files from the current directory
>>> par = MagicTs(field='par', iplot=False, all=True)
>>> # Time-average
>>> st = writeVpEq(par, tstart=2.1)
>>> print(st)
```

Parameters

- par (magic.MagicTs) a MagicTs object containing the par file
- **tstart** (float) the starting time of the averaging

Returns a formatted string

Return type str

magic.libmagic.zderavg(data, eta=0.35, spectral=True, colat=None, exclude=False) z derivative of an input array

```
>>> gr = MagiGraph()
>>> dvrdz = zderavg(gr.vr, eta=gr.radratio, colat=gr.colatitude)
```

Parameters

- data (numpy.ndarray) input array
- eta (float) aspect ratio of the spherical shell
- **spectral** (bool) when set to True use Chebyshev derivatives, otherwise use finite differences (default is True)
- **exclude** (bool) when set to True, exclude the first and last radial grid points and replace them by a spline extrapolation (default is False)
- colat (numpy.ndarray) colatitudes (when not specified a regular grid is assumed)

Returns the z derivative of the input array

Return type numpy.ndarray

DESCRIPTION OF THE FORTRAN MODULES

The following pages contain an exhaustive description of the different variables, subroutines and modules used in MagIC. This documentation is automatically generated from the source code docstrings using the Sphinx extention for the Fortran domain.

Fortran modules

- 1. For the main program file magic.f90, see here.
- 2. For the core modules that contain most of the global variables, see *here*.
- 3. For the MPI related modules, see *here*.
- 4. For the code initialization and the pre-calculations done in the initial stage of the computation (before the time-stepping loop), see *here* and *there*.
- 5. For the time-stepping loop, see *here*.
- 6. For the calculation of the non-linear terms (in the physical space) and their time-advance, see here.
- 7. For the calculation of the linear terms (in spectral space) and their time-advance, see *here*.
- 8. For the Chebyshev, Fourier and Legendre transforms, see *here*.
- 9. For the computation of the radial derivatives (Chebyshev) and the integration, see here.
- 10. For the definition of the blocking, see *here*.
- 11. For the calculation of the standard outputs (time-series, spectra and radial files), see here.
- 12. For the calculation of binary outputs (graphic files, movie files, potential and coeff files), see here.
- 13. For the additional calculations of specific outputs (torsional oscillations, RMS force balance, etc.), see here.
- 14. For reading and writing the check points (restart files), see *here*.
- 15. For additional useful functions (string manipulation, etc.), see *here*.

10.1 Main program magic.f90

program magic

A dynamic dynamo model driven by thermal convection in a rotating spherical fluid shell. This version can solve for both Boussinesq and anelastic fluids and non-dimensional variables are used throughout the whole code.

```
Use horizontal_data, rms (finalize_rms(), initialize_rms()),
```

```
(initialize_probes(),
                              finalize_probes()),
                                                        movie data
   (finalize movie data(),
                            initialize movie data()),
                                                        lmloop mod
   (finalize_lmloop(),
                           initialize_lmloop()),
                                                        lmloop_data
   (initialize_lmloop_data()), mem_alloc, init_fields,
                                                        radial der
   (finalize der arrays(), initialize der arrays()),
                                                             useful
   (abortrun()), precision mod,
                                  special (initialize grenoble(),
   finalize grenoble()),
                          fields average mod,
                                                   magnetic energy,
   step time mod
                       (step time(),
                                            initialize step time(),
   finalize_step_time()), communications (finalize_communications(),
   initialize_communications()), parallel_mod, precalculations,
                     physical_parameters,
                                                   radial functions
   num_param,
   (initialize_radial_functions(), finalize_radial_functions()),
   output_data (n_log_file(),
                                  tag(), log_file()),
   (initialize_output_power(), finalize_output_power()), namelists,
   outto_mod
               (initialize_outto_mod(),
                                             finalize_outto_mod()),
   torsional_oscillations,
                             timing
                                       (writetime(),
                                                      walltime()),
   kinetic energy, out coeff (finalize coeffs(), initialize coeffs()),
   blocking (finalize_blocking(), initialize_blocking()), constants
   (codeversion()), truncation, fieldslast, outrot (finalize outrot(),
   initialize_outrot()),
                                geos_mod
                                              (finalize_geos_mod(),
   initialize_geos_mod()),
                                    spectra (finalize_spectra(),
                            fields,
   initialize_spectra()),
                                             (initialize_dtb_mod(),
                                dtb_mod
   finalize_dtb_mod()),
                          outmisc_mod
                                           (finalize outmisc mod(),
   initialize_outmisc_mod()), radial_data (initialize_radial_data()),
   radialloop (finalize_radialloop(), initialize_radialloop()),
   outpar_mod (initialize_outpar_mod(), finalize_outpar_mod()), logic,
   start_fields(getstartfields())
Call to parallel(), walltime(), readnamelists(), initialize_output(),
   checktruncation(),
                                       initialize_memory_counter(),
                                          initialize_radial_data(),
   initialize_blocking(),
   initialize_lmloop_data(),
                                    initialize_radial_functions(),
   initialize_horizontal_data(), memwrite(), initialize_radialloop(),
   initialize_lmloop(),
                                            initialize_num_param(),
   initialize init fields(),
                                             initialize grenoble(),
                                           initialize_fieldslast(),
   initialize fields(),
   initialize_step_time(),
                                       initialize communications(),
   initialize_der_arrays(),
                                       initialize_kinetic_energy(),
   initialize_magnetic_energy(),
                                              initialize_spectra(),
   initialize outpar mod(),
                                          initialize outmisc mod(),
   initialize outrot(),
                                         initialize_output_power(),
   initialize coeffs(),
                                   initialize fields average mod(),
   initialize_to(),
                                             initialize_geos_mod(),
                           precalc(),
   initialize_outto_mod(),
                                           initialize_movie_data(),
   initialize_dtb_mod(),
                           initialize_probes(),
                                                  initialize_rms(),
   finalize_memory_counter(),
                                                  writenamelists(),
   getstartfields(), precalctimes(), writeinfo(), step_time(),
                                                    finalize_rms(),
   writetime(),
                      finalize_movie_data(),
   finalize_outto_mod(),
                           finalize_to(),
                                               finalize_geos_mod(),
   finalize_dtb_mod(),
                                     finalize_fields_average_mod(),
   finalize_coeffs(), finalize_output_power(), finalize_outrot(),
   finalize_outmisc_mod(), finalize_outpar_mod(), finalize_spectra(),
                                         finalize kinetic energy(),
   finalize magnetic energy(),
```

output_mod (finalize_output(), initialize_output()), probe_mod

10.2 Base modules

10.2.1 precision.f90

Description

This module controls the precision used in MagIC

Quick access

```
Variables sizeof_character, sizeof_logical, sizeof_integer, mpi_def_complex, mpi_out_real, mpi_def_real, lip, cp, outp, sizeof_def_complex, sizeof_out_real, sizeof_def_real
```

Needed modules

• mpimod: include "mpif.h"

Variables

- precision_mod/outp[integer,parameter=selected_real_kind(6)/public]
- precision_mod/mpi_out_real [integer,parameter=mpi_real4/public]
- precision_mod/sizeof_integer[integer,parameter=4/public]
- precision_mod/sizeof_character[integer,parameter=1/public]
- precision_mod/mpi_def_complex [integer,parameter=mpi_complex16/public]
- precision_mod/mpi_def_real [integer,parameter=mpi_real8/public]
- precision_mod/sizeof_def_real [integer,parameter=8/public]
- precision_mod/sizeof_logical [integer,parameter=2/public]
- precision_mod/sizeof_out_real[integer,parameter=4/public]
- precision_mod/lip[integer,parameter=selected_int_kind(12)/public]
- precision_mod/cp [integer,parameter=selected_real_kind(15)/public]
- precision_mod/sizeof_def_complex [integer,parameter=16/public]

10.2.2 truncation.f90

Description

This module defines the grid points and the truncation

Quick access

Variables ncp, fd_order, fd_order_bound, l_maxmag, lm_maxmag, lmagmem, ldtbmem, lmoviemem, lstressmem, n_r_ic_max_dtb, lm_max_dtb, lmp_max_dtb, n_phi_maxstr, n_r_max_dtb, n_r_maxstr, n_r_ic_maxmag, n_theta_maxstr, n_phi_max, minc, nalias, nrp, l_axi, l_max, n_cheb_max, n_m_max, m_max, n_r_totmag, n_cheb_ic_max, n_r_ic_max, lm_max_real, lmp_max, lm_max, n_phi_tot, n_r_max, n_theta_max, n_theta_axi, n_r_tot, radial_scheme, fd_ratio, fd_stretch

Routines checktruncation(), initialize_truncation()

Needed modules

- precision_mod (cp ()): This module controls the precision used in MagIC
- useful (abortrun ()): library with several useful subroutines
- logic(l_finite_diff()): Module containing the logicals that control the run

Variables

- truncation/n_r_ic_max [integer] number of grid points in inner core
- truncation/**1_max** [integer] max degree of Plms
- truncation/minc[integer] basic wavenumber, longitude symmetry
- truncation/n_cheb_ic_max [integer] number of chebs in inner core
- truncation/lstressmem[integer]

 Memory for stress output
- truncation/**l_axi** [logical] logical for axisymmetric calculations
- truncation/n_r_maxmag [integer]

 Number of radial points to calculate magnetic field
- truncation/n_phi_maxstr [integer]
 Number of phi points for stress output
- truncation/n_theta_max [integer] number of theta grid-points

- truncation/lm_maxmag [integer]

 Max. number of l/m combinations for magnetic field calculation
- truncation/n_r_ic_max_dtb [integer]

 Number of IC radial points for movie output
- truncation/ldtbmem[integer]

Memory for movie output

• truncation/fd_order[integer]

Finite difference order (for now only 2 and 4 are safe)

• truncation/radial_scheme [character] radial scheme (either Cheybev of FD)

- truncation/n_r_max [integer]
 number of radial grid points
- truncation/n_theta_maxstr [integer]

 Number of theta points for stress output
- truncation/**lmoviemem** [integer]

 Memory for movies
- truncation/nalias [integer] controls dealiasing in latitude
- truncation/n_phi_tot [integer] number of longitude grid points
- truncation/fd_ratio [real] drMin over drMax (only when FD are used)
- truncation/n_r_tot [integer] total number of radial grid points
- truncation/ncp [integer]
- truncation/lmp_max_dtb [integer]

 Number of l/m combinations for movie output if l runs to l_max+1
- truncation/fd_order_bound [integer]
 Finite difference order on the boundaries
- truncation/lmp_max[integer]
 number of l/m combination if l runs to l_max+1
- truncation/n_m_max [integer]
 max number of ms (different oders)
- truncation/m_max [integer] max order of Plms
- truncation/lm_max [integer] number of l/m combinations
- truncation/n_theta_axi [integer]
 number of theta grid-points (axisymmetric models)
- truncation/nrp [integer]
 dimension of phi points in for real/complex arrays
- truncation/lmagmem[integer]

 Memory for magnetic field calculation

- truncation/lm_max_real [integer]
 number of l/m combination for real representation (cos/sin)
- truncation/n_r_ic_maxmag [integer]

 Number of radial points to calculate IC magnetic field
- truncation/n_r_maxstr [integer]

 Number of radial points for stress output
- truncation/n_phi_max [integer] absolute number of phi grid-points
- truncation/n_r_max_dtb [integer]

 Number of radial points for movie output
- truncation/**1_maxmag** [integer]

 Max. degree for magnetic field calculation
- truncation/fd_stretch [real]
 regular intervals over irregular intervals
- truncation/lm_max_dtb [integer]

 Number of l/m combinations for movie output
- truncation/n_cheb_max [integer] max degree-1 of cheb polynomia

Subroutines and functions

```
{\bf subroutine} \ {\tt truncation/initialize\_truncation()}
```

Called from readnamelists()

subroutine truncation/checktruncation()

This function checks truncations and writes it into STDOUT and the log-file. MPI: called only by the processor responsible for output!

```
Called from magic
Call to abortrun()
```

10.2.3 num param.f90

Description

Module containing numerical and control parameters

Quick access

Variables n_lscale, n_tscale, ldif, ldifexp, n_cour_step, n_time_steps, istop, map_function, polo_flow_eq, thermo_variable, anelastic_flavour, amstart, pscale, difchem, difeta, difkap, difnu, enscale, escale, dtstart, alph2, alph1, lscale, dtmax, runtimelimit, dtmin, tend, timestart, runtime, tscale, intfac, alffac, courfac, vscale, runtimestart, alpha, delxh2, delxr2

```
Routines finalize_num_param(), initialize_num_param()
```

Needed modules

- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- precision mod: This module controls the precision used in MagIC
- truncation (n_r_max()): This module defines the grid points and the truncation

Variables

- num_param/amstart [real,public]
- num_param/n_cour_step [integer,public]
 Step for controlling Courant criteria
- num_param/alph1 [real,public]
 Input parameter for non-linear map to define degree of spacing (0.0:2.0)
- num_param/alph2 [real,public]
 Input parameter for non-linear map to define central point of different spacing (-1.0:1.0)
- num_param/n_time_steps [integer,public]
 Total number of time steps requested in the name list
- num_param/difnu [real,public]
 Amplitude of viscous hyperdiffusion
- num_param/timestart [real,public]

 Numerical time where run should start
- num_param/dtmin [real,public]

 Minimum allowed time step
- num_param/thermo_variable [character,public] thermodynamic variable: S or T
- num_param/delxr2 (:) [real,allocatable/public]
- num_param/ldifexp[integer,public]
 Exponent for hyperdiffusion function
- num_param/difkap [real,public]
 Amplitude of thermal hyperdiffusion
- num_param/dtstart [real,public]
 Initial time step if start solution is initialized
- num_param/difchem[real,public]
 Amplitude of chemical hyperdiffusion
- num_param/n_lscale [integer,public]
 Control length scale
- num_param/tend[real,public]

 Numerical time where run should end
- num_param/polo_flow_eq [character,public]
 form of the poloidal flow equation: Pressure or Double Curl

- num_param/runtimelimit (4) [integer,public]
 Maximum running time
- num_param/istop[integer,public]
 Variable used in FFT soubroutine
- num_param/ldif [integer,public]

 Degree where hyperdiffusion starts to act
- num_param/alffac [real,public]

 Value to scale Alfen-velocity in courant criteria
- num_param/anelastic_flavour [character,public] version of the anelastic approximation
- num_param/vscale [real,public]
 Velocity scale
- num_param/escale[real,public]
 Energy scale
- num_param/delxh2 (:) [real,allocatable/public]
- num_param/courfac [real,public]

 Value to scale velocity in courant criteria
- num_param/tscale [real,public]
 Time scale
- num_param/dtmax [real,public]

 Maximum allowed time step
- num_param/alpha [real,public]
 Weight for implicit time step
- num_param/n_tscale [integer,public]
 Control time scale
- num_param/pscale [real,public]
- num_param/runtimestart (4) [integer,public]
 Wall clock time of start of the run
- num_param/map_function [character,public]

 Mapping family: either tangent or arcsin
- num_param/difeta[real,public]
 Amplitude of magnetic hyperdiffusion
- num_param/enscale [real,public]
 Energies scale
- num_param/intfac [real,public]

 Value to re-scale dtMax during simulation
- num_param/runtime (4) [integer,public]
 Running time
- num_param/lscale [real,public]
 Length scale

Subroutines and functions

10.2.4 phys_param.f90

Description

Module containing the physical parameters

Quick access

Variables impxi, kbotb, kbots, kbotv, kbotxi, n_impxi, ktopp, ktopxi, ktops, imps, n_imps, imagcon, ktopb, mode, n_r_lcr, nvareps, nvarcond, nvardiff, nvarvisc, ktopv, nvarentropygrad, interior_model, ekscaled, rascaled, raxi, epss, dissnb, ek, con_lambdamatch, grunnb, epscxi0, epsc0, lffac, opr, osc, corfac, opm, o_sr, oek, conductance_ma, r_cut_model, po, po_diff, pr, prec_angle, diff_prec_angle, ohmlossfac, vischeatfac, r_lcr, buofac, chemfac, ra, epsc, epscxi, rho_ratio_ic, rho_ratio_ma, sc, g2, g0, g1, con_decrate, difexp, thexpnb, tmagcon, con_radratio, sigma_ratio, radratio, prmag, con_funcwidth, con_lambdaout, strat, polind, ampstrat, cmbhflux, rstrat, slopestrat, thickstrat, n_impxi_max, n_imps_max, peaks, peakxi, phis, phixi, thetas, thetaxi, widths, widthxi

Needed modules

• precision_mod: This module controls the precision used in MagIC

Variables

- physical_parameters/n_impxi [integer]
- physical_parameters/sigma_ratio [real]

 Value of IC rotation
- physical_parameters/ktopb [integer]
 Magnetic boundary condition
- physical_parameters/**strat** [real] number of density scale heights
- physical_parameters/ampstrat [real] stratified Layer
- physical_parameters/ekscaled[real] $E\,l^2$

```
• physical_parameters/n_imps[integer]
      Heat boundary condition
• physical_parameters/difexp[real]
      Thermal diffusivity variation
• physical parameters/ktopv[integer]
      Velocity boundary condition
• physical parameters/chemfac[real]
      Ratio of comp. Rayleigh number over Schmidt number
• physical_parameters/ktopp[integer]
      Boundary condition for spherically-symmetric pressure
• physical_parameters/ktops[integer]
      Entropy boundary condition
• physical_parameters/con_radratio[real]
      Transition between branches of electrical conductivity profile (nVarCond=1,2)
• physical_parameters/rho_ratio_ic [real]
      Same density as outer core
• physical_parameters/osc[real]
      Inverse of Schmidt number (i.e. chemical Prandtl number)
• physical parameters/pr[real]
      Prandtl number
• physical_parameters/rho_ratio_ma [real]
      Same density as outer core
• physical_parameters/ktopxi [integer]
      Boundary conditions for chemical composition
• physical_parameters/rstrat[real]
      stratified Layer
• physical_parameters/epsc[real]
      Renormalisation of epsc0
• physical_parameters/kbotxi[integer]
• physical_parameters/ohmlossfac[real]
      Prefactor for Ohmic heating: Di Pr/(Ra E Pm^2)
• physical_parameters/thetas(20)[real]
• physical_parameters/kbots[integer]
• physical_parameters/g2 [real]
      Set to 1.0 for 1/r^2 gravity
• physical_parameters/g1 [real]
      Set to 1.0 for linear gravity
• physical_parameters/g0 [real]
      Set to 1.0 for constant gravity
```

• physical_parameters/radratio [real]

• physical_parameters/nvarentropygrad[integer]

aspect ratio

stratified Layer

- physical_parameters/peakxi(20)[real]
- physical_parameters/con_funcwidth [real] nVarCond=1
- physical_parameters/kbotb [integer]
- physical_parameters/nvareps [integer]
 Selection of internal heating profile
- physical_parameters/**opm** [real]
 Inverse of magnetic Prandtl number
- physical_parameters/slopestrat [real] stratified Layer
- physical_parameters/nvarvisc[integer]
 Selection of variable viscosity profile
- physical_parameters/**prec_angle** [real]
 Precession angle
- physical_parameters/r_lcr [real]
 Radius beyond which conductivity is zero
- physical_parameters/**po_diff** [real]
 Poincaré number for differential precession
- physical_parameters/imps[integer]

 Heat boundary condition
- physical_parameters/prmag[real] magnetic Prandtl number
- physical_parameters/n_imps_max [integer,parameter=20]
 Heat boundary condition
- physical_parameters/**epscxi** [real]
 Renormalisation of epsc0Xi
- physical_parameters/corfac[real]
 Inverse of ekScaled
- physical_parameters/**po** [real]

 Poincaré number
- physical_parameters/mode [integer]

 Mode of calculation
- physical_parameters/interior_model [character] name of the interior model
- physical_parameters/tmagcon[real]
 Time for magnetoconvection calculation
- physical_parameters/raxi[real]
 Chemical composition-based Rayleigh number
- physical_parameters/ ${f rascaled}$ [real] $Ra\,l^3$
- physical_parameters/**dissnb** [real]
 Dissipation number

- physical_parameters/polind [real] polytropic index
- physical_parameters/lffac[real] Inverse of Pr*Ekman
- physical_parameters/**ek** [real] Ekman number
- physical parameters/kbotv[integer]
- physical_parameters/thetaxi (20) [real]
- physical_parameters/**epscxi0** [real]
 Internal chemical heat source magnitude
- physical_parameters/widthxi(20)[real]
- physical_parameters/**epsc0** [real]
 Internal heat source magnitude
- physical_parameters/ ${\bf vischeatfac}$ [real] Prefactor for viscous heating: $Di\,Pr/Ra$
- physical_parameters/thickstrat [real] stratified Layer
- physical_parameters/con_decrate [real]

 Slope of electrical conductivity profile (nVarCond=2)
- physical_parameters/conductance_ma [real]
 OC conductivity
- physical_parameters/cmbhflux [real] stratified Layer
- physical_parameters/**opr** [real]
 Inverse of Prandtl number
- physical_parameters/impxi [integer]
- physical_parameters/**grunnb** [real]
 Grüneisen paramater:math:'Gamma=(gamma-1)/alpha T\$
- physical_parameters/ra[real]
 Rayleigh number
- physical_parameters/n_r_lcr [integer]

 Number of radial points where conductivity is zero
- physical_parameters/o_sr[real]
 Inverse of sigma_ratio
- physical_parameters/nvardiff [integer]
 Selection of variable diffusivity profile
- physical_parameters/diff_prec_angle [real]

 Precession angle for differential precession
- physical_parameters/buofac [real]
 Ratio of Rayleigh number over Prandtl number

- physical_parameters/peaks (20) [real]
- physical_parameters/**oek** [real]
 Inverse of the Ekman number
- physical_parameters/**sc** [real]
 Schmidt number (i.e. chemical Prandtl number)
- physical_parameters/nvarcond[integer]
 Selection of variable conductivity profile
- physical_parameters/phixi (20) [real]
- physical_parameters/n_impxi_max [integer,parameter=20]
- physical_parameters/widths (20) [real]
- physical_parameters/con_lambdaout [real] nVarCond=1
- physical_parameters/**r_cut_model** [real]

 Percentage on the inner part of the interior model to be used
- physical_parameters/**phis** (20) [real]
- physical_parameters/imagcon [integer]
 Imposed magnetic field for magnetoconvection, at the boundaries
- physical_parameters/thexpnb [real] Thermal expansion * temperature $\alpha_0 T_0$
- physical_parameters/**epss** [real]

 Deviation from the adiabat

10.2.5 logic.f90

Description

Module containing the logicals that control the run

Quick access

Variables l_ab1, l_earth_likeness, l_single_matrix, l_cour_alf_damp, l_pressgraph, l_cmb_field, l_dt_cmb_field, l_corrmov, l rms. l_tomovie, l_to, l_runtimelimit, l_par, l_anel, l_anelastic_liquid, 1_am, l_probe, l_energy_modes, l_perppar, l_fluxprofs, l_average, 1 chemical conv, 1 cond ic, 1 cond ma, 1 correct amz, 1 correct ame, lverbose, l_viscbccalc, l_drift, l_dtbmovie, l_ht, l_htmovie, l_hel, l_iner, l_isothermal, l_rmagspec, l_dtrmagspec, l_b_nl_icb, l_b_nl_cmb, l_newmap, l_pv, l_power, l_r_fieldt, l_r_field, l_movie, l_movie_ic, l_movie_oc, l_z10mat, l_storepot, l_storetpot, l_storebpot, l_store_frame, l_2d_spectra, l_storevpot, l_time_hits, l_true_time, 1 lcr, 1 non adia, 1 rot ic, 1 mag 1f, 1 rot ma, 1 conv, 1 update s, 1_heat, l_update_b, l_mag, l_conv_nl, l_heat_nl, l_mag_nl, l_save_out, 1_corr, l_update_xi, l_update_v, l_mag_kin, $l_non_rot, l_dtb,$ l_sric, l_srma, l_diff_prec, l_finite_diff, l_precession, l_tp_form, l_double_curl, l_temperature_diff

Variables

• logic/l_time_hits [logical]
Switch for time for outputs

• logic/l_to[logical]

Switch for TO output in TOnhs.TAG, TOshs.TAG

• logic/l dtrmagspec[logical]

Switch for magnetic spectra at different depths at movie output times

• logic/l_lcr [logical]

Switch for zero electrical conductivity beyond r_LCR

• logic/l dtbmovie [logical]

Switch for dtB movie

• logic/lverbose [logical]

Switch for detailed information about run progress

• logic/l_correct_amz [logical]

Switch for correction of axial angular momentum

• logic/l_correct_ame [logical]

Switch for correction of equatorial angular mom.

• logic/l_pv [logical]

Switch for potential vorticity calculation

• logic/l_heat [logical]

Switch off heat terms calculation

• logic/l_srma [logical]

Switch to rotating OC with prescribed rot. rate

• logic/l_mag_lf[logical]

Switch off Lorentz force term

• logic/l_perppar [logical]

Switch for calculation of of kinetic energy perpendicular+parallel to the rotation axis

• logic/l_sric[logical]

Switch to rotating IC with prescribed rot. rate

• logic/l_mag[logical]

Switch off magnetic terms calculation

• logic/l_ab1 [logical]

1st order Adams Bashforth

• logic/l_non_rot [logical]

Switch to non-rotating

• logic/l_update_b [logical]

Switch off magnetic field update

• logic/l_r_fieldt [logical]

Switch for radial T coefficients

• logic/l_average [logical]

Switch for calculation of time-averages

• logic/l_update_v [logical]

Switch off velocity field update

- logic/l_cond_ic [logical]
 Switch for conducting IC
- logic/l_update_s [logical]
 Switch off entropy update
- logic/l_storevpot [logical]
 Switch for storing velocity field potentials
- logic/l_non_adia [logical]

 Switch in case the reference state is non-adiabatic
- logic/l_am [logical]
 Switch for angular momentum calculation
- logic/l_storebpot [logical]
 Switch for storing magnetic field potentials
- logic/l_viscbccalc [logical]
 Switch for dissipation layer for stress-free BCs plots
- logic/**l_conv** [logical]
 Switch off convection
- logic/l_pressgraph [logical]
 Store pressure in graphic files
- logic/l_true_time [logical]
 Switch for times of outputs
- logic/l_chemical_conv [logical]
 Switch for chemical convection
- logic/l_movie_ic [logical]
 Switch for recording of movie files for IC
- logic/l_2d_spectra [logical]
 Switch for storing of r-l-spectra
- logic/l_single_matrix [logical]
 In case entropy, w and P are solved at once implicitely
- logic/l_isothermal [logical]
 Switch for isothermal calculation
- logic/l_mag_nl [logical]
 Switch off non-linear magnetic terms calculation
- logic/l_z10mat [logical]
 Switch for solid body rotation
- logic/l_cour_alf_damp [logical]
 Modify Alven Courant condition based on Christensen et al., GJI, 1999 (.true. by default)
- logic/l_rmagspec [logical]
 Switch for magnetic spectra at different depths at log times
- logic/l_drift [logical]
 Switch for drift rates calculation
- logic/l_dt_cmb_field [logical]
 Switch for Bcoef files for secular variation of gauss coefs.

• logic/l_probe [logical]

Switch for artifical sensors

• logic/l_hel[logical]

Switch for helicity calculation, output in misc.TAG

• logic/l_corrmov[logical]

Switch for North/south correlation movie (see s_getEgeos.f)

• logic/l_finite_diff[logical]

Use finite differences for the radial scheme

• logic/l_newmap [logical]

Switch for non-linear mapping (see Bayliss and Turkel, 1990)

• logic/l_storetpot [logical]

Switch for storing entropy field potentials

• logic/l_cond_ma [logical]

Switch for conducting OC

• logic/l_save_out [logical]

Switch off outputs

• logic/l_rot_ic [logical]

Switch off IC rotation

• logic/l_anelastic_liquid[logical]

Switch for anelastic liquid calculation

• logic/l_double_curl [logical]

Use the double-curl of the NS equation to get the poloidal equation

• logic/l_b_nl_icb [logical]

Switch for non-linear magnetic field at IC

• logic/l_conv_nl [logical]

Switch off non-linear convection terms

• logic/l_htmovie [logical]

Switch for heat flux movie output

• logic/l_movie [logical]

Switch for recording of movie files

• logic/l_anel [logical]

Switch for anelastic calculation

• logic/l runtimelimit [logical]

Switch for absolute time limit of the run

• logic/l_fluxprofs [logical]

Switch for calculation of radial profiles of flux contributions

• logic/l_update_xi[logical]

Switch off update of chemical composition

• logic/l_earth_likeness[logical]

Compute the Earth-likeness of the CMB field following Christensen et al., EPSL, 2010

• logic/l_movie_oc[logical]

Switch for recording of movie files for OC

- logic/l_cmb_field [logical]
 Switch for Bcoef files for gauss coefficients
- logic/l_temperature_diff [logical] diffusion of temperature instead of entropy
- logic/l_precession [logical]
 Use precession
- logic/l_heat_nl [logical]
 Switch off non-linear heat terms calculation
- logic/l_iner [logical]
 Switch for inertial modes calculation
- logic/l_mag_kin [logical]
 Switch related for kinematic dynamo
- logic/l_rot_ma [logical]
 Switch off OC rotation
- logic/l_ht [logical]
 Switch for heat flux movie frame output
- logic/**1_storepot** [logical]
 Switch for storing all field potentials
- logic/l_tomovie [logical]
 Switch for TO movie output
- logic/l_power [logical]
 Switch for power budget terms calculation
- logic/l_diff_prec [logical]
 Use differential precession
- logic/l_dtb [logical]
 Switch to reserve memory for dtB movie
- logic/l_store_frame [logical]
 Switch for storing movie frames
- logic/l_par [logical]
 Switch for additional parameters calculation in s_getEgeos.f
- logic/l_b_nl_cmb [logical]
 Switch for non-linear magnetic field at OC
- logic/l_tp_form [logical]

 Use temperature and pressure instead of entropy and pressure
- logic/l_rms [logical]
 Switch for RMS force balances calculation
- logic/l_r_field [logical]
 Switch for radial coefficients
- logic/l_energy_modes [logical]
 Switch for calculation of distribution of energies over m's
- logic/l_corr [logical]
 Switch off rotation

10.2.6 fields.f90

Description

This module contains the potential fields and their radial derivatives

Quick access

Variables omega_ic, omega_ma, aj_ic, aj_ic_lmloc, b, b_ic, b_ic_lmloc, db_ic, db_ic_lmloc, ddb_ic, ddb_ic_lmloc, ddb_ic, ddj_ic, ddj_ic_lmloc, dj_ic, dj_ic_lmloc, work_lmloc, aj_lmloc, aj_rloc, b_lmloc, b_rloc, db_lmloc, db_rloc, ddb_lmloc, ddb_rloc, ddj_lmloc, ddw_lmloc, ddw_rloc, dj_lmloc, dj_rloc, dp_lmloc, dp_rloc, ds_lmloc, ds_rloc, dw_lmloc, dw_rloc, dxi_lmloc, dxi_rloc, dz_lmloc, dz_rloc, p_lmloc, p_rloc, s_lmloc, s_rloc, w_lmloc, w_rloc, xi_lmloc, xi_rloc, z_lmloc, z_rloc, field_lmloc_container, field_rloc_container, flow_lmloc_container, xi_lmloc_container, xi_rloc_container

Routines finalize_fields(), initialize_fields()

Needed modules

- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- lmloop_data(ulmmag(), llmmag(), llm(), ulm())
- radial_data(nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- precision_mod: This module controls the precision used in MagIC
- parallel_mod (rank ()): This module contains the blocking information
- logic (l_chemical_conv()): Module containing the logicals that control the run
- truncation(lm_max(), lm_maxmag(), n_r_ic_maxmag(), n_r_max(), n_r_maxmag()): This module defines the grid points and the truncation

Variables

- fields/aj_lmloc(:,:) [complex,pointer/public]
- fields/s_rloc_container(:,:,:) [complex,target/allocatable/public]
- fields/b_rloc(:,:) [complex,pointer/public]
- fields/ddw_rloc(:,:) [complex,pointer/public]
- fields/dxi_rloc(:,:) [complex,pointer/public]
- fields/aj_ic(:,:) [complex,allocatable/public]
- fields/ddw_lmloc(:,:) [complex,pointer/public]
- fields/xi_lmloc_container(:,:,:) [complex,target/allocatable/public]

- fields/xi_rloc_container(:,:,:) [complex,target/allocatable/public]
- fields/dj_lmloc(:,:) [complex,pointer/public]
- fields/dw_rloc(:,:) [complex,pointer/public]
- fields/p_rloc(:,:) [complex,pointer/public]
- fields/dp_rloc(:,:) [complex,pointer/public]
- fields/field_lmloc_container(:,:,:) [complex,target/allocatable/public]
- fields/db_lmloc(:,:) [complex,pointer/public]
- fields/s_lmloc(:,:) [complex,pointer/public]
- fields/**s_rloc**(:,:) [complex,pointer/public]
- fields/ddb_lmloc(:,:) [complex,pointer/public]
- fields/b_ic(:,:) [complex,allocatable/public]
- fields/ds_lmloc(:,:) [complex,pointer/public]
- fields/dj_rloc(:,:) [complex,pointer/public]
- fields/ddb_ic_lmloc(:,:) [complex,allocatable/public]
- fields/p_lmloc(:,:) [complex,pointer/public]
- fields/dxi_lmloc(:,:) [complex,pointer/public]
- fields/db_ic_lmloc(:,:) [complex,allocatable/public]
- fields/xi_rloc(:,:) [complex,pointer/public]
- fields/dw_lmloc(:,:) [complex,pointer/public]
- fields/dp_lmloc(:,:) [complex,pointer/public]
- fields/dj_ic_lmloc(:,:) [complex,allocatable/public]
- fields/ddb_ic(:,:) [complex,allocatable/public]
- fields/db_ic(:,:) [complex,allocatable/public]
- fields/s_lmloc_container(:,:,:) [complex,target/allocatable/public]
- fields/flow_lmloc_container(:,:,:) [complex,target/allocatable/public]
- fields/work_lmloc(:,:) [complex,allocatable/public]
- fields/dj_ic(:,:) [complex,allocatable/public]
- fields/b lmloc(:,:) [complex,pointer/public]
- fields/**z_rloc**(:,:) [complex,pointer/public]
- fields/flow_rloc_container(:,:,:) [complex,target/allocatable/public]
- fields/**z_lmloc**(:,:) [complex,pointer/public]
- fields/dz_rloc(:,:) [complex,pointer/public]
- fields/field_rloc_container(:,:,:) [complex,target/allocatable/public]
- fields/ds_rloc(:,:) [complex,pointer/public]
- fields/omega_ma [real,public]
- fields/w_lmloc(:,:) [complex,pointer/public]

- fields/aj_rloc(:,:) [complex,pointer/public]
- fields/b(:,:) [complex,allocatable/public]
- fields/ddj_ic_lmloc(:,:) [complex,allocatable/public]
- fields/ddj_ic(:,:) [complex,allocatable/public]
- fields/b_ic_lmloc(:,:) [complex,allocatable/public]
- fields/ddb_rloc(:,:) [complex,pointer/public]
- fields/db_rloc(:,:) [complex,pointer/public]
- fields/w_rloc(:,:) [complex,pointer/public]
- fields/aj_ic_lmloc(:,:) [complex,allocatable/public]
- fields/xi_lmloc(:,:) [complex,pointer/public]
- fields/omega_ic[real,public]
- fields/ddj_lmloc(:,:) [complex,pointer/public]
- fields/dz_lmloc(:,:) [complex,pointer/public]

Subroutines and functions

10.2.7 dt fieldsLast.f90

Description

This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.

The variables labeled with a suffix 'Last' are provided by the restart file for the first time step or calculated here or by the update routines for the following time step. These fields remain in the LM-distributed space

Quick access

```
Variables d_omega_ic_dtlast, d_omega_ma_dtlast, lorentz_torque_iclast,
    lorentz_torque_malast, dbdt_iclast_lmloc, dbdtlast_lmloc,
    djdt_iclast_lmloc, djdtlast_lmloc, dpdtlast_lmloc, dsdtlast_lmloc,
    dwdtlast_lmloc, dxidtlast_lmloc, dzdtlast_lo
Routines finalize_fieldslast(), initialize_fieldslast()
```

Needed modules

- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- lmloop_data(ulmmag(), llmmag(), llm(), ulm())
- precision_mod: This module controls the precision used in MagIC
- logic(l_chemical_conv()): Module containing the logicals that control the run
- truncation (lm_max(), lm_maxmag(), n_r_ic_maxmag(), n_r_max(), n_r_maxmag()): This module defines the grid points and the truncation
- parallel_mod (rank ()): This module contains the blocking information

Variables

- fieldslast/dbdt_iclast_lmloc(:,:) [complex,allocatable/public]
- fieldslast/djdtlast_lmloc(:,:) [complex,allocatable/public]
- fieldslast/dpdtlast_lmloc(:,:) [complex,allocatable/public]
- fieldslast/lorentz_torque_malast [real,public]
- fieldslast/dwdtlast_lmloc(:,:) [complex,allocatable/public]
- fieldslast/dzdtlast_lo(:,:) [complex,allocatable/public]
- fieldslast/lorentz_torque_iclast [real,public]
- fieldslast/djdt_iclast_lmloc(:,:) [complex,allocatable/public]
- fieldslast/d_omega_ma_dtlast [real,public]
- fieldslast/d_omega_ic_dtlast [real,public]
- fieldslast/dxidtlast_lmloc(:,:) [complex,allocatable/public]
- fieldslast/dsdtlast_lmloc(:,:) [complex,allocatable/public]
- fieldslast/dbdtlast_lmloc(:,:) [complex,allocatable/public]

Subroutines and functions

10.2.8 output_data.f90

Description

This module contains the parameters for output control

Quick access

Variables graph_mpi_fh, l_graph_time, l_max_cmb, l_max_r, m_max_modes, n_bpot_step, n_bpots, n_cmb_step, n_cmbs, n_coeff_r_max, n_graph_file, n_graph_step, n_graphs, n_log_file, n_log_step, n_logs, n_movie_frames, n_movie_step , n_pot_step , n_pots , n_probe_out , n_probe_step , n_r_field_step, n_r_fields, n_r_step, n_rst_step, n_rsts, n_spec_step, n_specs, n_stores, n_t_bpot, n_t_cmb, n_t_graph, n_t_log, n_t_movie, n_t_pot, n_t_probe, n_t_r_field, n_t_rst, n_t_spec, n_t_to, n_t_tomovie, n_t_toz, n_t_tpot, n_t_vpot, n_to_step, n_tomovie_frames, n_tomovie_step, n_tos, n_toz_step, n_tozs, n_tpot_step, n_tpots, n_vpot_step, n_vpots, l_max_comp, n_time_hits, n_coeff_r, tag, runid, graph_file, log_file, lp_file, n_r_array, dt_bpot, dt_cmb, dt_graph, dt_log, dt_movie, dt_pot, dt_probe, dt_r_field, dt_rst, dt_spec, dt_to, dt_tomovie, dt_toz, dt_tpot, dt_vpot, rcut, rdea, sdens, t_bpot_start, t_bpot_stop, t_cmb_start, t_cmb_stop, t_graph_start, t_graph_stop, t_log_start, t_log_stop, t_movie_start, t_movie_stop, t_pot_start, t_pot_stop, t_probe_start, t_probe_stop, t_r_field_start, t_r_field_stop, t_rst_start, t_rst_stop, t_spec_start, t_spec_stop, t_to_start, t_to_stop, t_tomovie_start, t_tomovie_stop, t_toz_start, t_toz_stop, t_tpot_start, t_tpot_stop, t_vpot_start, t_vpot_stop, zdens, t_bpot, t_cmb, t_graph, t_log, t_movie, t_pot, t_probe, t_r_field, t_rst, t_spec, t_to, t_tomovie, t_toz, t_tpot, t_vpot

Needed modules

• precision_mod: This module controls the precision used in MagIC

Variables

- output_data/n_tozs[integer,public]
- output_data/n_graphs [integer,public]
- output_data/t_toz_start [real,public]
- output_data/n_tpots [integer,public]
- output_data/runid[character,public]
- output_data/dt_spec [real,public]
- output_data/dt_tpot [real,public]
- output_data/dt_probe [real,public]
- output_data/n_r_step[integer,public]
- output_data/t_movie_start [real,public]
- output_data/n_t_toz [integer,public]
- output_data/n_t_cmb [integer, public]
- output_data/sdens[real,public]
- output_data/n_tpot_step[integer,public]
- output_data/n_t_spec [integer,public]

- output_data/t_rst_start [real,public]
- output_data/n_time_hits [integer,parameter=5000/public]
- output_data/t_bpot_start [real,public]
- output_data/dt_graph [real,public]
- output_data/dt_tomovie [real,public]
- output_data/t_rst_stop [real,public]
- output_data/t_vpot_start [real,public]
- output_data/n_r_array (100) [integer,public]
- output_data/n_t_tomovie [integer,public]
- output_data/l_max_cmb [integer,public]
- output_data/n_to_step[integer,public]
- output_data/n_log_step[integer,public]
- output_data/t_to_stop [real,public]
- output_data/t_rst (5000) [real,public]
- output_data/t_log_stop [real,public]
- output_data/dt_cmb [real,public]
- output_data/n_cmb_step [integer,public]
- output_data/l_graph_time [logical,public]
- output_data/dt_r_field[real,public]
- output_data/t_probe (5000) [real, public]
- output_data/t_graph_start [real,public]
- output_data/dt_vpot [real,public]
- output_data/l_max_comp [integer,public]

 Maximum spherical harmonic degree to estimate Earth-likeness
- output_data/dt_log[real,public]
- output_data/t_cmb (5000) [real,public]
- output_data/t_probe_start [real,public]
- output_data/n_t_pot [integer,public]
- output_data/n_graph_step [integer,public]
- output_data/n_t_bpot [integer,public]
- output_data/zdens [real,public]
- output_data/t_graph (5000) [real,public]
- output_data/t_to_start [real,public]
- output_data/dt_toz [real,public]
- output_data/n_bpots [integer,public]
- output_data/dt_movie [real,public]

- output_data/graph_mpi_fh [integer,public]
- output_data/t_r_field_stop [real,public]
- output_data/n_log_file [integer,public]
- output_data/n_movie_frames [integer,public]
- output_data/n_specs [integer,public]
- output_data/t_cmb_start [real,public]
- output_data/t_tomovie_stop [real,public]
- output_data/t_r_field_start [real,public]
- output_data/n_probe_step[integer,public]
- output_data/n_tos[integer,public]
- output_data/n_rst_step [integer,public]
- output_data/**dt_pot** [real,public]
- output_data/t_vpot (5000) [real,public]
- output_data/n_graph_file [integer,public]
- output_data/n_vpot_step[integer,public]
- output_data/t_spec_stop [real,public]
- output_data/t_tpot_start [real,public]
- output_data/n_t_movie [integer,public]
- output_data/n_t_to[integer,public]
- output_data/n_t_probe [integer,public]
- output_data/n_tomovie_step[integer,public]
- output_data/t_cmb_stop [real,public]
- output_data/n_vpots[integer,public]
- output_data/t_log_start [real,public]
- output_data/t_toz_stop [real,public]
- output_data/t_to (5000) [real,public]
- output_data/n_tomovie_frames [integer,public]
- output_data/n_pots [integer,public]
- output_data/t_tpot (5000) [real,public]
- output_data/n_rsts[integer,public]
- output_data/n_cmbs [integer,public]
- output_data/n_t_graph [integer,public]
- output_data/dt_rst [real,public]
- output_data/t_tomovie_start [real,public]
- output_data/t_toz (5000) [real,public]
- output_data/dt_to [real,public]

- output_data/n_stores[integer,public]
- output_data/n_t_vpot [integer,public]
- output_data/t_pot_start [real,public]
- output_data/m_max_modes [integer,public]
- output_data/n_coeff_r (:) [integer,allocatable/public]
- output data/t spec(5000)[real,public]
- output_data/n_logs [integer,public]
- output_data/t_movie (5000) [real,public]
- output_data/n_t_tpot [integer,public]
- output_data/t_tpot_stop[real,public]
- output_data/n_t_log[integer,public]
- output_data/l_max_r [integer,public]
- output_data/n_r_fields [integer,public]
- output_data/n_movie_step[integer,public]
- output_data/t_r_field(5000)[real,public]
- output_data/n_t_r_field[integer,public]
- output_data/n_pot_step [integer,public]
- output_data/n_probe_out [integer,public]
- output_data/t_pot (5000) [real,public]
- output_data/t_graph_stop [real,public]
- output_data/t_probe_stop[real,public]
- output_data/n_r_field_step[integer,public]
- output_data/rcut [real,public]
- output_data/t_movie_stop [real,public]
- output_data/tag[character,public]
- output_data/n_toz_step[integer,public]
- output_data/n_coeff_r_max [integer,public]
- output_data/n_bpot_step [integer,public]
- output_data/lp_file [character,public]
- output_data/t_log (5000) [real,public]
- output_data/t_spec_start [real,public]
- output_data/n_t_rst[integer,public]
- output_data/graph_file [character,public]
- output_data/n_spec_step[integer,public]
- output_data/t_bpot_stop [real,public]
- output_data/t_bpot (5000) [real,public]

- output_data/t_tomovie (5000) [real, public]
- output_data/dt_bpot [real,public]
- output_data/t_pot_stop [real,public]
- output_data/t_vpot_stop [real,public]
- output_data/log_file [character,public]
- output data/rdea[real,public]

10.2.9 constants f90

Description

module containing constants and parameters used in the code.

Quick access

```
Variables c_dt_z10_ic, c_dt_z10_ma, c_lorentz_ic, c_lorentz_ma, c_z10_omega_ic, c_z10_omega_ma, y10_norm, y11_norm, mass, c_moi_ic, c_moi_ma, c_moi_oc, surf_cmb, vol_ic, vol_oc, codeversion, zero, ci, half, sin60, one, two, three, four, pi, third, osq4pi, cos36, cos72, sin36, sin72, sq4pi
```

Needed modules

• precision_mod: This module controls the precision used in MagIC

Variables

- constants/ci [complex,parameter=(0.0_cp,1.0_cp)]
- constants/c_z10_omega_ma[real]
- constants/c_lorentz_ic [real]
- constants/one [real,parameter=1.0_cp]
- constants/**four** [real,parameter=4.0_cp]
- constants/sin60 [real,parameter=0.5_cp*sqrt(3.0_cp)]
- constants/**zero** [complex,parameter=(0.0_cp,0.0_cp)]
- constants/**surf_cmb** [real]

 Outer boundary surface
- constants/c_moi_oc [real]
 Moment of inertia of the outer core
- constants/three [real,parameter=3.0_cp]
- constants/c_dt_z10_ic[real]
- constants/c_z10_omega_ic[real]

- constants/c_moi_ic [real]

 Moment of inertia of the inner core
- constants/c_moi_ma [real]

 Moment of inertia of the mantle
- constants/pi [real,parameter=4.0_cp*atan(1.0_cp)]
- constants/osq4pi [real,parameter=1.0_cp/sq4pi]
- constants/cos36 [real,parameter=cos(36.0_cp*pi/180.0_cp)]
- constants/y10_norm[real]
- constants/cos72 [real,parameter=cos(72.0_cp*pi/180.0_cp)]
- constants/sin72 [real,parameter=sin(72.0_cp*pi/180.0_cp)]
- constants/c_dt_z10_ma [real]
- constants/**two** [real,parameter=2.0_cp]
- constants/half [real,parameter=0.5_cp]
- constants/vol_oc [real]
 Volume of the outer core
- constants/vol_ic [real]
 Volume of the inner core
- constants/y11_norm[real]
- constants/**sq4pi** [real,parameter=sqrt(4.0_cp*pi)]
- constants/c_lorentz_ma [real]
- constants/third[real,parameter=0.3333333333333]
- constants/codeversion[character,parameter='5.6']
- constants/sin36 [real,parameter=sin(36.0_cp*pi/180.0_cp)]
- constants/mass [real]

 Mass of the outer core

10.2.10 special.f90

Description

This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes

Quick access

```
Variables lgrenoble, n_imp, l_ri, l_imp, m_riicasym, m_riicsym, m_rimaasym, m_rimasym, l_curr, bic, amp_riicasym, amp_riicsym, amp_rimaasym, amp_rimasym, amp_curr, amp_imp, expo_imp, omega_riicasym, omega_riicsym, omega_rimaasym, omega_rimasym, bmax_imp, rrmp, b0, db0, ddb0, fac_loop
```

Routines finalize_grenoble(), initialize_grenoble()

Needed modules

- precision_mod: This module controls the precision used in MagIC
- truncation (n_r_maxmag()): This module defines the grid points and the truncation

Variables

- special/amp_rimaasym [real, public]
 Amplitude of forcing at the outer boundary (eq anti symm)
- special/l_ri [logical,public]

 Decide whether to use inertial-mode forcing
- special/amp_riicsym[real,public]
 Amplitude of forcing at the inner boundary (eq symm)
- special/lgrenoble [logical, public]
- special/m_riicasym[integer,public]

 Order of forcing at the inner boundary (eq anti symm)
- special/amp_curr [real,public]
 Amplitude of magnetic field of current loop
- special/m_rimaasym[integer,public]
 Order of forcing at the outer boundary (eq anti symm)
- special/fac_loop(:) [real,allocatable/public]
- special/b0 (:) [real, allocatable/public]
- special/amp_riicasym [real,public]
 Amplitude of forcing at the inner boundary (eq anti symm)
- special/db0 (:) [real,allocatable/public]
- special/ddb0 (:) [real, allocatable/public]
- special/expo_imp [real,public]
 Exponent for decay
- special/amp_imp [real,public]
 Amplitude of the time varying osc
- special/omega_riicsym[real,public]
 Frequency of forcing at the inner boundary (eq symm)
- special/bmax_imp [real,public]
 Location of maximum in g_ext/g_int
- special/**1_curr** [logical,public]
 Switch for current loop at the equator
- special/m_rimasym[integer,public]
 Order of forcing at the outer boundary (eq symm)
- special/omega_riicasym[real,public]
 Frequency of forcing at the inner boundary (eq anti symm)
- special/bic[real,public]

- special/omega_rimaasym [real,public]
 Frequency of forcing at the outer boundary (eq anti symm)
- special/omega_rimasym[real,public]
 Frequency of forcing at the outer boundary (eq symm)
- special/m_riicsym [integer, public]
 Order of forcing at the inner boundary (eq symm)
- special/**rrmp** [real,public]
 Magnetopause radius
- special/n_imp [integer,public]
 Controls external field model
- special/l_imp [integer,public]

 Mode of external field (dipole,quadrupole etc.)
- special/amp_rimasym[real,public]
 Amplitude of forcing at the outer boundary (eq symm)

Subroutines and functions

10.3 MPI related modules

10.3.1 parallel.f90

Description

This module contains the blocking information

Quick access

Needed modules

- omp_lib
- mpi

Variables

```
• parallel_mod/nr_on_last_rank [integer]
```

- parallel_mod/rank_with_l1m0 [integer]
- parallel_mod/nthreads [integer]
- parallel_mod/rank_bn [integer]
- parallel_mod/n_procs [integer]
- parallel_mod/nlmbs_per_rank [integer]
- parallel_mod/ierr[integer]
- parallel_mod/nr_per_rank [integer]
- parallel_mod/chunksize [integer]

Subroutines and functions

10.3.2 radial data.f90

Description

This module defines the MPI decomposition in the radial direction.

Quick access

```
Variables n_r_cmb, n_r_icb, nrstart, nrstartmag, nrstop, nrstopmag

Routines initialize_radial_data()
```

Needed modules

- parallel_mod (nr_on_last_rank(), nr_per_rank(), n_procs(), rank()): This module contains the blocking information
- logic (l_finite_diff(), l_mag(), lverbose()): Module containing the logicals that control the run
- truncation (n_r_max()): This module defines the grid points and the truncation

Variables

```
• radial_data/n_r_cmb [integer,public]
```

- radial_data/n_r_icb [integer, public]
- radial_data/nrstopmag[integer,public]
- radial_data/nrstartmag[integer,public]
- radial_data/nrstop[integer,public]
- radial_data/nrstart[integer,public]

Subroutines and functions

```
subroutine radial_data/initialize_radial_data()
```

This subroutine is used to set up the MPI decomposition in the radial direction

Called from magic

10.3.3 LMLoop_data.f90

Quick access

```
Variables 11m, 11mmag, 1m_on_last_rank, 1m_per_rank, ulm, ulmmag
```

Routines initialize_lmloop_data()

Needed modules

- parallel_mod(n_procs(), nlmbs_per_rank(), rank()): This module contains the blocking information
- blocking (sizelmb(), nlmbs(), lmstartb(), lmstopb()): Module containing blocking information
- logic (l_mag()): Module containing the logicals that control the run

Variables

- lmloop_data/llmmag[integer,public]
- lmloop_data/lm_per_rank [integer,public]
- lmloop_data/lm_on_last_rank[integer,public]
- lmloop_data/ulmmag[integer,public]
- lmloop_data/llm[integer,public]
- lmloop_data/ulm[integer,public]

Subroutines and functions

10.3.4 communications.f90

Quick access

```
Variables get_global_sum, r_lm_gather_type,
                                          r_lm_gather_type_lm_end,
   final_wait_array,
                      r_request, s_request,
                                                 array_of_statuses,
   r_transfer_type, r_transfer_type_nr_end,
                                                    s_transfer_type,
   s_transfer_type_nr_end,
                                               r_transfer_type_cont,
   r_transfer_type_nr_end_cont,
                                               s_transfer_type_cont,
   s_transfer_type_nr_end_cont, gt_cheb, gt_ic, gt_oc, lo2r_field,
   102r_flow, 102r_s, 102r_xi, r21o_b, r21o_flow, r21o_s, r21o_xi,
   temp_gather_lo, temp_r2lo
Routines initialize communications(),
                                           finalize communications(),
   scatter_from_rank0_to_lo(), lm2lo_redist(), gather_from_lo_to_rank0(),
   1021m_redist(), destroy_gather_type(), destroy_r21m_type(),
   destroy_lm2r_type(), lm2r_redist_wait(),
                                                r2lm_redist_wait(),
                                               lm2r_redist_start(),
   lo2r_redist_wait(),
                        r2lo_redist_wait(),
   gather_all_from_lo_to_rank0(),
                                                 lo2r_redist_start(),
   r2lm_redist_start(), r2lo_redist_start(), create_lm2r_type(),
   create_r2lm_type(),
                         create_gather_type(),
                                                      myallgather(),
   get_global_sum_cmplx_1d(),
                                          get_global_sum_cmplx_2d(),
   get_global_sum_real_2d()
```

Needed modules

- mem_alloc(memwrite(), bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (abortrun ()): library with several useful subroutines
- lmloop_data(llm(), ulm())
- radial_data(nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- precision_mod: This module controls the precision used in MagIC
- parallel_mod (nr_on_last_rank(), nr_per_rank(), n_procs(), ierr(), rank()): This module contains the blocking information
- logic (l_double_curl(), l_chemical_conv(), l_mag_kin(), l_heat(), l_tp_form(), l_mag(), l_conv()): Module containing the logicals that control the run
- blocking (lo_map(), lmstartb(), st_map(), lmstopb()): Module containing blocking information
- mpimod: include "mpif.h"
- truncation (n_r_ic_max(), l_max(), minc(), l_axi(), n_r_max(), lm_max()): This module defines the grid points and the truncation

Types

```
• type communications/unknown_type
```

Type fields

- % count [integer]
- % temp_rloc(,,*)[complex,pointer]
- % r_request (*) [integer,allocatable]
- % arr_rloc (,,*) [complex,pointer]
- % final_wait_array (*) [integer,allocatable]
- % s_request (*) [integer,allocatable]
- type communications/unknown_type

Type fields

- % count [integer]
- % s_request (*) [integer, allocatable]
- % final_wait_array (*) [integer,allocatable]
- % temp_rloc(,,*)[complex,pointer]
- % r_request (*) [integer,allocatable]
- type communications/unknown_type

Type fields

- % dim2 [integer]
- % gather_mpi_type (*) [integer,allocatable]

Variables

- communications/r2lo_xi[r2lm_type,public]
- communications/s_transfer_type_cont(:,:) [integer,private/allocatable/save]
- communications/r2lo_flow[r2lm_type,public]
- communications/gt_ic[gather_type,public]
- communications/gt_oc[gather_type,public]
- $\bullet \verb| communications/get_global_sum|[public]|$
- communications/s_transfer_type(:)[integer,private/allocatable/save]
- communications/array_of_statuses(:,:) [integer,private/allocatable]
- communications/r_lm_gather_type [integer,private]
- communications/s_transfer_type_nr_end_cont(:,:) [integer,private/allocatable/save]
- communications/r_request(:) [integer,private/allocatable]
- communications/r_transfer_type(:)[integer,private/allocatable/save]
- communications/final_wait_array(:) [integer,private/allocatable]

- communications/s_request(:)[integer,private/allocatable]
- communications/r_transfer_type_cont (:,:) [integer,private/allocatable/save]
- communications/r2lo_s [r2lm_type,public]
- communications/r_transfer_type_nr_end_cont(:,:) [integer,private/allocatable/save]
- communications/lo2r xi[lm2r type,public]
- communications/lo2r flow [lm2r type,public]
- communications/lo2r_field[lm2r_type,public]
- communications/**r2lo_b** [r2lm_type,public]
- communications/r_transfer_type_nr_end(:) [integer,private/allocatable/save]
- communications/s_transfer_type_nr_end(:) [integer,private/allocatable/save]
- communications/**gt_cheb** [gather_type,public]
- communications/r_lm_gather_type_lm_end[integer,private]
- communications/lo2r_s [lm2r_type,public]
- communications/temp_r2lo(:,:) [complex,private/allocatable]
- communications/temp_gather_lo(:) [complex,private/allocatable]

Subroutines and functions

```
//so low-order digits of y are lost.
            c = (t - sum) - y //(t - sum) recovers the high-order part of y;
                                  //subtracting y recovers -(low part of y)
            sum = t
                                  //Algebraically, c should always be zero.
                                  //Beware eagerly optimising compilers!
            //Next time around, the lost low part will be added to y in a fresh.
          \rightarrowattempt.
         return sum
         Parameters arr_local (*) [complex,in]
         Return global_sum [real]
subroutine communications/gather_all_from_lo_to_rank0 (self, arr_lo, arr_full)
         Parameters
              • self [gather_type]
              • arr_lo (ulm-(llm)+1,self%dim2) [complex]
              • arr_full (lm_max,self%dim2) [complex]
         Called from fields_average(), store(), write_movie_frame(), output(),
             dtb_gather_lo_on_rank0(), costf_arrays()
subroutine communications/create_gather_type (self, dim2)
         Define the datatypes for gather_all_from_lo_to_rank0 the sending array has dimension
         (llm:ulm,1:dim2) receiving array has dimension (1:lm max,1:dim2)
         Parameters
              • self [gather_type]
              • dim2 [integer]
         Called from initialize_communications()
subroutine communications/destroy_gather_type (self)
         Parameters self [gather_type]
         Called from finalize_communications()
subroutine communications/gather_from_lo_to_rank0 (arr_lo, arr_full)
         Parameters
              • arr lo (ulm-(llm)+1) [complex]
              • arr full (lm max) [complex]
         Called from fields_average(), write_pot(), get_e_mag(), write_coeff_r(),
             output(), write_bcmb()
subroutine communications/scatter from rank0 to lo(arr full, arr lo)
         Parameters
              • arr_full (lm_max) [complex]
              • arr_lo (ulm-(llm)+1) [complex]
```

Called from step_time(), readstartfields_old(), readstartfields()

```
subroutine communications/create_lm2r_type(self[, count])
         Parameters self [lm2r_type]
         Options count [integer,in,optional]
         Called from initv(), initialize_communications()
subroutine communications/destroy lm2r type(self)
         Parameters self [lm2r type]
         Called from initv(), finalize_communications()
subroutine communications/create_r2lm_type(self[, count])
         Parameters self [r2lm_type]
         Options count [integer,in,optional]
         Called from initv(), initialize_dtb_mod(), initialize_communications()
subroutine communications/destroy_r2lm_type (self)
         Parameters self [r2lm_type]
         Called from finalize_dtb_mod(), initv(), finalize_communications()
subroutine communications/lm2r_redist_start (self, arr_lmloc, arr_rloc)
         Parameters
              • self [lm2r type]
              • arr_lmloc (ulm-(llm)+1,n_r_max,*) [complex,in]
              • arr_rloc (lm_max,nrstop-(nrstart)+1,*) [complex,out]
         Called from 1o2r redist start()
subroutine communications/lm2r_redist_wait (self)
         Parameters self [lm2r_type]
         Called from lo2r_redist_wait()
subroutine communications/lo2r redist start(self, arr lo, arr rloc)
         Parameters
              • self [lm2r_type]
              • arr_lo (ulm-(llm)+1,n_r_max,*) [complex,in]
              • arr_rloc (lm_max,nrstop-(nrstart)+1,*) [complex,out,target]
         Called from getstartfields(), initv(), lmloop()
         Call to lm2r_redist_start()
subroutine communications/lo2r_redist_wait (self)
         Parameters self [lm2r_type]
         Called from step_time(), initv()
         Call to lm2r_redist_wait()
subroutine communications/r2lm_redist_start (self, arr_rloc, arr_lmloc)
         Parameters
```

```
• self [r2lm_type]
               • arr_rloc (lm_max,nrstop-(nrstart)+1,*) [complex,in]
               • arr_lmloc (ulm-(llm)+1,n_r_max,*) [complex,out]
         Called from r2lo_redist_start()
subroutine communications/r2lm redist wait(self)
         Parameters self [r2lm type]
         Called from r2lo_redist_wait()
subroutine communications/r2lo_redist_start (self, arr_rloc, arr_lo)
         Parameters
               • self [r2lm_type]
               • arr_rloc (lm_max,nrstop-(nrstart)+1,*) [complex,in]
               • arr_lo (ulm-(llm)+1,n_r_max,*) [complex,out]
         Called from step_time(), initv(), dtb_from_rloc_to_lo()
         Call to r2lm_redist_start()
subroutine communications/r2lo_redist_wait(self)
         Parameters self [r2lm type]
         Called from step_time(), initv(), dtb_from_rloc_to_lo()
         Call to r2lm_redist_wait()
subroutine communications/lm2lo_redist(arr_lmloc, arr_lo)
         Parameters
               • arr_lmloc (ulm-(llm)+1,n_r_max) [complex,in]
               • arr_lo (ulm-(llm)+1,n_r_max) [complex,out]
         Call to abortrun()
subroutine communications/lo21m redist(arr lo, arr lmloc)
         Parameters
               • arr_lo (ulm-(llm)+1,n_r_max) [complex,in]
               • arr_lmloc (ulm-(llm)+1,n_r_max) [complex,out]
         Call to abortrun()
subroutine communications/myallgather(arr, dim1, dim2)
         Parameters
               • arr (dim1,dim2) [complex,inout]
               • dim1 [integer,in,]
               • dim2 [integer,in,]
         Use parallel_mod, blocking
```

10.4 Code initialization

10.4.1 Namelists.f90

Description

Read and print the input namelist

Quick access

Routines readnamelists(), defaultnamelists(), writenamelists()

Needed modules

- torsional_oscillations: This module contains information for TO calculation and output
- useful (abortrun()): library with several useful subroutines
- special: This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- probe_mod
- movie_data(movie(), n_movies(), n_movies_max())
- output_data: This module contains the parameters for output control
- logic: Module containing the logicals that control the run
- precision_mod: This module controls the precision used in MagIC
- *init_fields*: This module is used to construct the initial solution.
- parallel_mod: This module contains the blocking information
- num_param: Module containing numerical and control parameters
- physical_parameters: Module containing the physical parameters
- charmanip (capitalize(), length_to_blank()): This module contains several useful routines to manipule character strings
- truncation: This module defines the grid points and the truncation
- blocking (cacheblock_size_in_b()): Module containing blocking information
- constants: module containing constants and parameters used in the code.
- radial_functions: This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

Subroutines and functions

```
subroutine namelists/readnamelists()
```

Purpose of this subroutine is to read the input namelists. This program also determins logical parameters that

are stored in logic.f90.

Called from magic

```
Call to defaultnamelists(), abortrun(), length_to_blank(), capitalize(),
   initialize truncation()
```

subroutine namelists/writenamelists(n out)

Purpose of this subroutine is to write the namelist to file unit n_out. This file has to be open before calling this routine.

Parameters n_out [integer,in]

Called from magic

Call to length_to_blank()

subroutine namelists/defaultnamelists()

Purpose of this subroutine is to set default parameters for the namelists.

Called from readnamelists()

10.4.2 startFiels.f90

Quick access

```
Variables deltaxicond, botcond, topcond, botxicond, topxicond, deltacond Routines getstartfields()
```

Needed modules

- readcheckpoints (readstartfields(), readstartfields_old()): This module contains the functions that can help reading and mapping of the restart files
- fieldslast: This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- radial_der (get_dr(), get_ddr()): Radial derivatives functions
- useful (logwrite(), cc2real()): library with several useful subroutines
- parallel_mod(n_procs(), nlmbs_per_rank(), rank()): This module contains the blocking information
- communications (lo2r_field(), lo2r_xi(), lo2r_flow(), lo2r_redist_start(), lo2r_s())
- fields: This module contains the potential fields and their radial derivatives
- logic (l_rot_ic(), l_chemical_conv(), l_anelastic_liquid(), l_tp_form(), l_z10mat(), l_lcr(), l_mag_kin(), l_mag(), l_heat(), l_srma(), l_mag_lf(), l_single_matrix(), l_rot_ma(), l_temperature_diff(), l_sric(), l_cond_ic(), l_conv()): Module containing the logicals that control the run
- lmloop_data(llmmag(), lm_per_rank(), lm_on_last_rank(), ulm(), llm(), ulmmag())
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.

- precision_mod: This module controls the precision used in MagIC
- init_fields (initxi(), pt_cond(), initb(), init_b1(), l_start_file(), tops(), start_file(), initv(), xi_cond(), inits(), init_xi1(), init_s1(), ps_cond(), topxi()): This module is used to construct the initial solution.
- radial_der_even(get_ddr_even())
- special (lgrenoble()): This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- num_param (alpha(), dtmax()): Module containing numerical and control parameters
- constants (one (), osq4pi(), c_lorentz_ic(), two(), zero(), c_lorentz_ma()): module containing constants and parameters used in the code.
- physical_parameters (imps(), lffac(), impxi(), kbotv(), vischeatfac(), n_r_lcr(), ktopv(), imagcon(), interior_model(), thexpnb(), epss()): Module containing the physical parameters
- truncation: This module defines the grid points and the truncation
- blocking (nlmbs(), lmstartb(), lo_map(), lmstopb()): Module containing blocking information
- mpimod: include "mpif.h"
- radial_functions (rscheme_oc(), orhol(), dr_fac_ic(), rhol(), dlalphal(), alphal(), orl(), dltempl(), beta(), r(), templ(), chebt_ic_even(), otempl(), ogrun(), chebt_ic()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

- start_fields/botcond [real,public]
 Conducting heat flux at the inner boundary
- start_fields/topcond [real,public]
 Conducting heat flux at the outer boundary
- start_fields/botxicond [real,public]
 Conducting mass flux at the inner boundary
- start_fields/**deltacond** [real,public]
 Temperature or entropy difference between boundaries
- start_fields/deltaxicond [real,public]
 Composition difference between boundaries
- start_fields/topxicond[real,public]
 Conducting mass flux at the outer boundary

Subroutines and functions

```
subroutine start_fields/getstartfields(time, dt, dtnew, n_time_step)
```

Purpose of this subroutine is to initialize the fields and other auxiliary parameters.

Parameters

• time [real,out]

- **dt** [real,out]
- dtnew [real,out]
- **n_time_step** [integer,out]

Called from magic

10.4.3 init_fields.f90

Description

This module is used to construct the initial solution.

Quick access

Variables init_b1, init_s1, init_s2, init_v1, init_xi1, init_xi2, nrotic, nrotma, inform, l_reset_t, l_start_file, n_s_bounds, n_xi_bounds, start_file, amp_b1, amp_s1, amp_s2, amp_v1, amp_xi1, amp_xi2, bpeakbot, bpeaktop, omega_diff, omega_ic1, omega_ic2, omega_ma1, omega_ma2, omegaosz_ic1, omegaosz_ic2, omegaosz_ma1, omegaosz_ma2, scale_b, scale_s, scale_v, scale_xi, tomega_ic1, tomega_ic2, tomega_ma1, tomega_ma2, tshift_ic1, tshift_ic2, tshift_ma1, tshift_ma2, tipdipole, bots, botxi, tops, topxi, s_top, xi_top, s_bot, xi_bot

Routines initialize_init_fields(), finalize_init_fields(), initb(), j_cond(), inits(), ps_cond(), pt_cond(), initv(), initxi(), xi_cond()

Needed modules

- horizontal_data (hdif_b(), phi(), dthetala(), dlh(), dthetals(), d_lp1(), sintheta(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel_mod: This module contains the blocking information
- cosine_transform_odd
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- algebra (prepare_mat(), solve_mat())
- fft: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- physical_parameters (n_imps(), n_impxi(), sigma_ratio(), diff_prec_angle(), thetaxi(), buofac(), vischeatfac(), ktopp(), ktops(), osc(), impxi(), ktopxi(), epsc(), kbotxi(), o_sr(), thetas(), widthxi(), kbots(), peaks(), opr(), radratio(), peakxi(), oek(), opm(), phixi(), imps(), n_impxi_max(), n_imps_max(), epscxi(), widths(), phis(), imagcon(), thexpnb()): Module containing the physical parameters
- lmloop_data(ulmmag(), llmmag(), llm(), ulm())

- radial_data(n_r_cmb(), nrstart(), n_r_icb(), nrstop()): This module defines the MPI decomposition in the radial direction.
- precision_mod: This module controls the precision used in MagIC
- communications (r2lo_redist_start(), lo2r_redist_wait(), create_lm2r_type(), r2lm_type(), destroy_r2lm_type(), lm2r_type(), destroy_lm2r_type(), create_r2lm_type(),lo2r_redist_start(),r2lo_redist_wait())
- legendre grid to spec(legtf1())
- logic (l_rot_ic(), l_anelastic_liquid(), l_tp_form(), l_chemical_conv(), l_cond_ic(), l_srma(), l_rot_ma(), l_non_adia(), l_temperature_diff(), l_sric(), l_diff_prec()): Module containing the logicals that control the run
- useful (abortrun(), random()): library with several useful subroutines
- radial_functions (jvarcon(), rho0(), or2(), or3(), or1(), ogrun(), temp0(), otemp1(), d2cheb_ic(), ddltemp0(), dlalpha0(), dlkappa(), cheb_norm_ic(), dllambda(), dcheb_ic(), rgrav(), orho1(), cheb_ic(), alpha0(), dltemp0(), beta(), chebt_ic(), kappa(), r_cmb(), epscprof(), dbeta(), r_ic(), r(), rscheme_oc(), r_icb(), ddlalpha0(), lambda()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (lmstartb(), nthetabs(), sizethetab(), nfs(), lmstopb(), lo_map(), st_map()): Module containing blocking information
- constants (osq4pi(), third(), y10_norm(), c_z10_omega_ma(), two(), one(), four(), zero(), c_z10_omega_ic(), three(), half(), pi()): module containing constants and parameters used in the code.
- truncation (n_r_ic_max(), n_r_tot(), n_cheb_ic_max(), minc(), n_phi_max(), l_max(), lmp_max(), l_axi(), n_r_max(), m_max(), lm_max(), nrp(), n_r_maxmag(), n_theta_max()): This module defines the grid points and the truncation

Variables

- init_fields/tshift_ma1 [real, public]
- init_fields/tshift_ma2 [real,public]
- init_fields/amp_b1 [real,public]
- init fields/scale s[real, public]
- init_fields/**s_bot** (80) [real,public] input variables for tops,bots
- init_fields/init_b1 [integer,public]
- init_fields/omegaosz_ic2[real,public]
- init_fields/n_s_bounds [integer,parameter=20/public]
- init_fields/omegaosz_ic1 [real,public]
- init_fields/**l_reset_t** [logical,public] reset time from startfile ?
- init_fields/tomega_ma1 [real,public]
- init fields/tomega ma2 [real, public]

- init_fields/xi_top(80)[real,public]
- init_fields/scale_xi [real,public]
- init_fields/scale_b [real, public]
- init_fields/omega_diff[real,public]
- init_fields/1_start_file [logical,public] taking fields from startfile?
- init_fields/omega_ic1 [real,public]
- init_fields/omega_ic2 [real,public]
- init_fields/init_v1 [integer,public]
- init_fields/scale_v [real, public]
- init_fields/amp_v1 [real,public]
- init_fields/init_s1[integer,public]
- init_fields/**tipdipole** [real,public] adding to symetric field
- init_fields/init_xi1 [integer,public]
- init_fields/tomega_ic2 [real,public]
- init_fields/tomega_ic1 [real,public]
- init_fields/init_xi2 [integer,public]
- init_fields/tops (:,:) [complex,allocatable/public]
- init_fields/nrotma[integer,public]
- init_fields/omega_ma1 [real,public]
- init_fields/omega_ma2 [real,public]
- init_fields/**xi_bot** (80) [real,public] input variables for topxi,botxi
- init_fields/bpeaktop[real,public]
- init_fields/tshift_ic2 [real,public]
- init_fields/tshift_ic1 [real,public]
- init_fields/s_top (80) [real, public]
- init_fields/amp_xi2 [real,public]
- init_fields/topxi(:,:) [complex,allocatable/public]
- init_fields/n_xi_bounds [integer,parameter=20/public]
- init_fields/amp_xi1 [real, public]
- init_fields/inform[integer,public]
 format of start file
- init_fields/bpeakbot [real, public]
- init_fields/botxi(:,:) [complex,allocatable/public]
- init_fields/amp_s2 [real,public]

- init_fields/omegaosz_ma1 [real,public]
- init_fields/omegaosz_ma2 [real,public]
- init_fields/amp_s1 [real,public]
- init_fields/init_s2 [integer,public]
- init_fields/bots(:,:) [complex,allocatable/public]
- init fields/nrotic[integer,public]
- init_fields/**start_file** [character,public] name of start file

Subroutines and functions

Purpose of this subroutine is to initialize the velocity field So far it is only rudimentary and will be expanded later. Because s is needed for dwdt init_s has to be called before.

Parameters

- w (ulm-(llm)+1,n_r_max) [complex,inout]
- **z** (ulm-(llm)+1,n_r_max) [complex,inout]
- omega_ic [real,out]
- omega_ma [real,out]

Called from getstartfields()

```
Call to create_r2lm_type(), create_lm2r_type(), lo2r_redist_start(),
    lo2r_redist_wait(), fft_thetab(), legtf1(), r2lo_redist_start(),
    r2lo_redist_wait(), destroy_r2lm_type(), destroy_lm2r_type(),
    random()
```

```
subroutine init_fields/inits(s, p)
```

Purpose of this subroutine is to initialize the entropy field according to the input control parameters.

Input	value
init_s1	random noise initialized the noise spectrum decays as 1 ^ (init_s1-1) with peak ampli-
< 100:	tude amp_s1 for l=1
init_s1	a specific harmonic mode initialized with amplitude amp_s1. init_s1 is interpreted as
>=100:	number llmm where ll: harmonic degree, mm: harmonic order.
init_s2	a second harmonic mode initialized with amplitude amp_s2. init_s2 is again inter-
>100:	preted as number llmm where ll: harmonic degree, mm: harmonic order.

Parameters

- **s** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*inout*]
- **p** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*inout*]

Called from getstartfields()

Call to pt_cond(), ps_cond(), random(), abortrun(), fft_thetab(), legtf1(),
 prepare_mat()

```
subroutine init_fields/initxi(xi)
```

Purpose of this subroutine is to initialize the chemical composition according to the input control parameters.

Input	value
init_xi1	random noise initialized the noise spectrum decays as 1^ (init_xi1-1) with peak ampli-
< 100:	tude amp_xi1 for l=1
init_xi1	a specific harmonic mode initialized with amplitude amp_xi1. init_xi1 is interpreted
>=100:	as number llmm where ll: harmonic degree, mm: harmonic order.
init_xi2	a second harmonic mode initialized with amplitude amp_xi2. init_xi2 is again inter-
>100 :	preted as number llmm where ll: harmonic degree, mm: harmonic order.

Parameters xi $(ulm-(llm)+1, n \ r \ max)$ [complex,inout]

```
Called from getstartfields()
```

```
Call to xi_cond(), random(), abortrun(), fft_thetab(), legtf1(),
    prepare_mat()
```

```
subroutine init_fields/initb(b, aj, b_ic, aj_ic, lorentz_torque_ic, lorentz_torque_ma)
```

Purpose of this subroutine is to initialize the magnetic field according to the control parameters imageon and init_b1/2. In addition CMB and ICB peak values are calculated for magneto convection.

Parameters

- **b** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,inout]
- **aj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,inout]
- **b_ic** (ulmmag-(llmmag)+1,n_r_ic_max) [complex,inout]
- **aj_ic** (*ulmmag-(llmmag)+1,n_r_ic_max*) [*complex,inout*]
- lorentz_torque_ic [real,out]
- lorentz_torque_ma [real,out]

Called from getstartfields()

Call to j_cond(), abortrun(), random()

subroutine init_fields/j_cond(lm0, aj0, aj0_ic)

Purpose of this subroutine is to solve the diffusion equation for an initial toroidal magnetic field.

Parameters

- lm0 [integer,in]
- **aj0** (*) [complex,out]

```
• aj0_ic (*) [complex,out]

Called from initb()
```

Call to prepare_mat(), abortrun()

```
subroutine init_fields/xi_cond(xi0)
```

Purpose of this subroutine is to solve the chemical composition equation for an the conductive (1=0,m=0)-mode. Output is the radial dependence of the solution in s0.

```
Parameters xi0 (*) [real,out]
```

 $\textbf{Called from} \ \textit{getstartfields(), initxi()} \\$

Call to prepare_mat(), abortrun()

```
subroutine init_fields/pt_cond(t0, p0)
```

Purpose of this subroutine is to solve the entropy equation for an the conductive (l=0,m=0)-mode. Output is the radial dependence of the solution in t0 and p0.

Parameters

- **t0** (*) [real,out]
- **p0** (*) [real,out]

Called from getstartfields(), inits()

Call to prepare_mat(), abortrun()

```
subroutine init_fields/ps_cond(s0, p0)
```

Purpose of this subroutine is to solve the entropy equation for an the conductive (l=0,m=0)-mode. Output is the radial dependence of the solution in s0 and p0.

Parameters

- **s0** (*) [real,out]
- **p0** (*) [real,out]

Called from getstartfields(), inits()

Call to prepare_mat(), abortrun()

10.5 Pre-calculations

10.5.1 preCalc.f90

Quick access

Routines precalc(), writeinfo(), get_hit_times(), precalctimes()

Needed modules

- horizontal_data (horizontal()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel_mod (rank ()): This module contains the blocking information
- useful (abortrun (), logwrite ()): library with several useful subroutines
- output_data: This module contains the parameters for output control
- logic (l_time_hits(), l_to(), l_newmap(), l_storetpot(), l_heat(), l_mag_lf(), l_mag(), l_non_rot(), l_anelastic_liquid(), l_tomovie(), l_cond_ic(), l_storevpot(), l_anel(), l_non_adia(), l_storevpot(), l_probe(), l_lcr(), l_movie(), l_cmb_field(), l_chemical_conv(), l_precession(), l_storepot(), l_r_field(), l_diff_prec(), l_save_out(), l_temperature_diff(), l_dt cmb_field()): Module containing the logicals that control the run
- integration (rint_r()): Radial integration functions
- precision_mod: This module controls the precision used in MagIC
- init_fields (s_top(), omega_diff(), topxi(), n_xi_bounds(), tops(), s_bot(), botxi(), l_reset_t(), xi_bot(), n_s_bounds(), bots(), xi_top()): This module is used to construct the initial solution.
- special (fac_loop(), l_curr()): This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- num_param: Module containing numerical and control parameters
- physical_parameters (polind(), lffac(), ek(), epsc0(), tmagcon(), ktops(), epscxi0(), rho_ratio_ic(), osc(), pr(), sigma_ratio(), ktopxi(), epsc(), chemfac(), kbotxi(), ra(), n_r_lcr(), o_sr(), rho_ratio_ma(), nvardiff(), po(), diff_prec_angle(), buofac(), kbots(), opr(), radratio(), oek(), sc(), nvareps(), opm(), nvarvisc(), raxi(), prmag(), r_lcr(), epscxi(), corfac(), mode(), interior_model(), nvarcond(), ekscaled(), prec_angle(), rascaled()): Module containing the physical parameters
- radial_functions (rho0(), dlvisc(), temp0(), ogrun(), rscheme_oc(), dlkappa(), transportproperties(), dllambda(), rgrav(), r_surface(), alpha0(), dltemp0(), beta(), divktemp0(), kappa(), visc(), r_cmb(), dbeta(), r(), radial(), r_icb(), dentropy0(), sigma(), lambda()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- constants: module containing constants and parameters used in the code.
- truncation(n_r_ic_max(), n_cheb_ic_max(), minc(), n_phi_max(), l_max(), nalias(), n_r_max(), m_max(), lm_max(), n_cheb_max(), n_theta_max()): This module defines the grid points and the truncation

Variables

Subroutines and functions

```
subroutine precalculations/precalc()
```

Purpose of this subroutine is to initialize the calc values, arrays, constants that are used all over the code. The stuff is stored in the common blocks. MPI: This is called by every processors.

10.5. Pre-calculations 227

```
Called from magic
          Call to radial(),
                               transportproperties(), horizontal(), rint_r(),
               abortrun(), logwrite()
subroutine precalculations/precalctimes (time, n_time_step)
          Precalc. after time, time and dthas been read from startfile.
          Parameters
                 • time [real,out]
                 • n_time_step [integer,out]
          Called from magic
          Call to get_hit_times()
subroutine precalculations/get_hit\_times(t, n\_t\_max, n\_t, l\_t, t\_start, t\_stop, dt, n\_tot,
                                                        n_step, string_bn, time, tscale)
          Parameters
                 • t (n_t_max) [real,inout] :: Times for output
                 • n_t_max [integer,in,] :: Dimension of t(*)
                 • n_t [integer,out] :: No. of output times
                 • l_t [logical,out] :: =.true. if output times are defined
                 • t_start [real,inout] :: Starting time for output
                 • t_stop [real,inout] :: Stop time for output
                 • dt [real,inout] :: Time step for output
                 • n_tot [integer, inout] :: No. of output (times) if no times defined
                 • n_step [integer,inout] :: Ouput step in no. of time steps
                 • string_bn [character,in]
                 • time [real,in] :: Time of start file
                 • tscale [real,in]
          Called from precalctimes ()
          Call to abortrun()
subroutine precalculations/writeinfo(n_out)
          Purpose of this subroutine is to write the namelist to file unit n out. This file has to be open before
          calling this routine.
          Parameters n_out [integer,in]
          Called from magic
```

Call to abortrun()

10.5.2 radial.f90

Description

This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Quick access

```
Variables ndd_costf1, ndd_costf1_ic, ndd_costf2_ic, ndi_costf1_ic, ndi_costf2_ic, chebt_ic, chebt_ic_even, cheb_norm_ic, dr_fac_ic, r_icb, alpha2, alpha1, r_cmb, r_surface, d2temp0, alpha0, beta, cheb_int, cheb_int_ic, dbeta, ddbeta, ddlalpha0, ddltemp0, ddlvisc, dentropy0, divktemp0, dlalpha0, dlkappa, dllambda, dltemp0, dlvisc, epscprof, jvarcon, kappa, lambda, o_r_ic, o_r_ic2, ogrun, or1, or2, or3, or4, orho1, orho2, otemp1, r, r_ic, rgrav, rho0, sigma, temp0, visc, cheb_ic, d2cheb_ic, dcheb_ic
```

```
Routines finalize_radial_functions(), initialize_radial_functions(), transportproperties(), radial(), getentropygradient(), polynomialbackground(), getbackground()
```

Needed modules

- chebyshev (type_cheb_odd())
- parallel_mod (rank ()): This module contains the blocking information
- cosine_transform_odd
- useful (abortrun(), logwrite()): library with several useful subroutines
- algebra (prepare_mat(), solve_mat())
- output_data(tag()): This module contains the parameters for output control
- finite_differences (type_fd()): This module is used to calculate the radial grid when finite differences are requested
- radial_der (get_dr()): Radial derivatives functions
- radial_scheme (type_rscheme()): This is an abstract type that defines the radial scheme used in MagIC
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- num_param (alph1 (), alph2 ()): Module containing numerical and control parameters
- cosine_transform_even
- logic(l_newmap(), l_anelastic_liquid(), l_finite_diff(), l_temperature_diff(), l_mag(), l_heat(), l_single_matrix(), l_anel(), l_non_adia(), l_tp_form(), l_cond_ic(), l_isothermal()): Module containing the logicals that control the run
- chebyshev_polynoms_mod
- physical_parameters: Module containing the physical parameters
- constants (four (), three (), two (), sq4pi (), half (), one ()): module containing constants and parameters used in the code.

10.5. Pre-calculations 229

• truncation (n_r_ic_max(), fd_order(), n_r_max(), fd_stretch(), fd_order_bound(), n_cheb_max(), fd_ratio()): This module defines the grid points and the truncation

Variables

- radial_functions/**r**(:)[real,allocatable/public]
- radial_functions/cheb_norm_ic [real,public]
 Chebyshev normalisation for IC
- radial_functions/or4 (:) [real,allocatable/public]
- radial_functions/rho0 (:) [real,allocatable/public]
- radial_functions/or2 (:) [real,allocatable/public]
- radial_functions/or3(:)[real,allocatable/public]
- radial_functions/or1 (:) [real, allocatable/public]
- radial_functions/otemp1 (:) [real,allocatable/public]
- radial_functions/temp0 (:) [real,allocatable/public]
- radial_functions/dentropy0 (:) [real,allocatable/public]
- radial_functions/o_r_ic(:) [real,allocatable/public]
- radial_functions/ogrun (:) [real,allocatable/public]
- radial_functions/**dbeta**(:)[real,allocatable/public]
- radial_functions/alpha2 [real,public]
 Input parameter for non-linear map to define central point of different spacing (-1.0:1.0)
- radial_functions/**ddltemp0** (:) [real,allocatable/public]
- radial_functions/alpha1 [real,public]
 Input parameter for non-linear map to define degree of spacing (0.0:2.0)
- radial_functions/dlalpha0(:) [real, allocatable/public]
- radial_functions/**dlkappa** (:) [real,allocatable/public]
- radial_functions/ndd_costf1 [integer,public]
 Radii for transform
- radial_functions/jvarcon(:)[real,allocatable/public]
- radial_functions/ndi_costf2_ic [integer,public]
 Radii for transform
- radial_functions/**dllambda**(:)[real,allocatable/public]
- radial_functions/**dcheb_ic**(:,:) [real,allocatable/public]
- radial_functions/rgrav(:)[real,allocatable/public]
- radial_functions/**cheb_int**(:)[real,allocatable/public]
- radial_functions/**r_surface** [real,public]
 Surface radius for extrapolation
- radial_functions/cheb_int_ic(:) [real,allocatable/public]
- radial_functions/**d2cheb_ic**(:,:) [real,allocatable/public]

```
• radial_functions/orho1 (:) [real,allocatable/public]
```

- radial_functions/**ddlvisc**(:) [real,allocatable/public]
- radial_functions/d2temp0(:)[real,allocatable/private]
- radial_functions/cheb_ic(:,:) [real,allocatable/public]
- radial_functions/ $dr_fac_ic[real,public]$ For IC: $2/(2r_i)$
- radial_functions/ndi_costfl_ic[integer,public]
 Radii for transform
- radial_functions/alpha0(:)[real,allocatable/public]
- radial_functions/**dltemp0** (:) [real,allocatable/public]
- radial_functions/**beta**(:)[real,allocatable/public]
- radial_functions/chebt_ic_even [costf_even_t,public]
- radial_functions/ddbeta(:)[real,allocatable/public]
- radial_functions/**ddlalpha0** (:) [real,allocatable/public]
- radial_functions/**chebt_ic** [costf_odd_t,public]
- radial_functions/divktemp0 (:) [real,allocatable/public]
- radial_functions/r_ic(:) [real,allocatable/public]
- radial_functions/kappa (:) [real,allocatable/public]
- radial_functions/r_cmb [real,public]OC radius
- radial_functions/**visc**(:) [real,allocatable/public]
- radial_functions/o_r_ic2 (:) [real, allocatable/public]
- radial_functions/epscprof(:) [real,allocatable/public]
- radial_functions/ndd_costf2_ic [integer,public]
 Radii for transform
- radial_functions/orho2 (:) [real,allocatable/public]
- radial_functions/**dlvisc**(:) [real,allocatable/public]
- radial_functions/r_icb [real,public]
 IC radius
- radial_functions/ndd_costf1_ic [integer,public]
 Radii for transform
- radial_functions/**sigma** (:) [real,allocatable/public]
- radial_functions/lambda (:) [real,allocatable/public]

Subroutines and functions

```
\begin{tabular}{ll} \textbf{subroutine} & \texttt{radial\_functions/initialize\_radial\_functions} () \\ & \textbf{Initial memory allocation} \end{tabular}
```

Called from magic

10.5. Pre-calculations 231

```
subroutine radial functions/finalize radial functions()
          Called from magic
subroutine radial_functions/radial()
     Calculates everything needed for radial functions, transforms etc.
          Called from precalc()
          Call to getentropygradient(), getbackground(), polynomialbackground(),
              logwrite(), cheb_grid(), get_chebs_even()
subroutine radial_functions/transportproperties()
     Calculates the transport properties: electrical conductivity, kinematic viscosity and thermal conductivity.
          Called from precalc()
          Call to abortrun()
subroutine radial_functions/getentropygradient()
     This subroutine allows to calculate the background entropy gradient in case stable stratification is required
          Called from radial()
subroutine radial functions/getbackground(input, boundaryval, output, coeff)
          Linear solver of the form: df/dx +coeff*f= input with f(1)=boundaryVal
          Parameters
               • input (n_r_max) [real,in]
               • boundaryval [real,in]
               • output (n_r_max) [real,out]
          Options coeff (n\_r\_max) [real,in,optional]
          Called from radial()
          Call to prepare_mat(), abortrun()
subroutine radial_functions/polynomialbackground(coeffdens, coefftemp[, coeffgrav])
          This subroutine allows to calculate a reference state based on an input polynomial function.
          Parameters
               • coeffdens (*) [real,in]
               • coefftemp (*) [real,in]
          Options coeffgrav (*) [real,in,optional]
          Called from radial()
10.5.3 horizontal f90
```

Description

Module containing functions depending on longitude and latitude plus help arrays depending on degree and order

Quick access

Variables 1modd, 1moddp, 1start, 1startp, 1stop, 1stopp, n_theta_cal2ord, cosn2, costheta, d_1, d_1p1, d_m, d_mc2m, dlh, dphi, dphi0, dphi02, dpl0eq, dtheta1a, dtheta1s, dtheta2a, dtheta2s, dtheta3a, dtheta3s, dtheta4a, dtheta4s, gauss, hdif_b, hdif_s, hdif_v, hdif_xi, o_sin_theta, o_sin_theta_e2, osn1, osn2, phi, sintheta, sn2, theta, theta_ord, dplm, plm, wdplm, wplm

```
Routines initialize_horizontal_data(), finalize_horizontal_data(), horizontal(), qauleg()
```

Needed modules

- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- fft: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- num_param (difchem(), difeta(), difnu(), ldif(), ldifexp(), difkap()): Module containing numerical and control parameters
- precision_mod: This module controls the precision used in MagIC
- plms_theta(plm_theta())
- logic(l_rms(), l_non_rot()): Module containing the logicals that control the run
- physical_parameters (ek()): Module containing the physical parameters
- truncation (l_max(), minc(), n_phi_max(), lmp_max(), l_axi(), n_m_max(), m_max(), lm_max(), n_theta_max()): This module defines the grid points and the truncation
- blocking (1mp21(), 1m2m(), 1m21(), 1mp21m()): Module containing blocking information
- constants (zero(), pi(), two(), half(), one()): module containing constants and parameters used in the code.
- radial_functions (r_cmb ()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

- horizontal_data/dplm(:,:) [real,allocatable/public]
- horizontal_data/dphi02(:)[complex,allocatable/public]
- horizontal_data/osn1 (:) [real,allocatable/public]
- horizontal_data/osn2 (:) [real,allocatable/public]
- horizontal_data/sn2 (:) [real,allocatable/public]
- horizontal_data/o_sin_theta(:)[real,allocatable/public]
- horizontal_data/dphi(:) [complex,allocatable/public]
- horizontal_data/lstopp(:)[integer,allocatable/public]
- horizontal_data/hdif_xi(:) [real,allocatable/public]
- horizontal_data/costheta(:)[real,allocatable/public]

10.5. Pre-calculations 233

- horizontal_data/hdif_b (:) [real, allocatable/public]
- horizontal_data/lstop(:)[integer,allocatable/public]
- horizontal_data/dphi0 (:) [complex,allocatable/public]
- horizontal_data/dtheta4a (:) [real,allocatable/public]
- horizontal_data/lmodd(:)[logical,allocatable/public]
- horizontal data/dlh(:)[real,allocatable/public]
- horizontal_data/dtheta3s(:) [real,allocatable/public]
- horizontal_data/dtheta2a(:)[real,allocatable/public]
- horizontal_data/hdif_s (:) [real,allocatable/public]
- horizontal_data/hdif_v(:) [real,allocatable/public]
- horizontal_data/dtheta4s(:)[real,allocatable/public]
- horizontal_data/theta(:)[real,allocatable/public]
- horizontal_data/dtheta2s(:)[real,allocatable/public]
- horizontal_data/lstart(:) [integer,allocatable/public]
- horizontal_data/phi(:) [real,allocatable/public]
- horizontal_data/theta_ord(:) [real,allocatable/public]
- horizontal_data/d_mc2m(:) [real,allocatable/public]
- horizontal_data/plm(:,:) [real,allocatable/public]
- horizontal_data/o_sin_theta_e2 (:) [real,allocatable/public]
- horizontal_data/gauss (:) [real,allocatable/public]
- horizontal_data/wplm(:,:) [real,allocatable/public]
- horizontal_data/d_lp1 (:) [real,allocatable/public]
- horizontal_data/lstartp(:)[integer,allocatable/public]
- horizontal_data/dtheta3a(:)[real,allocatable/public]
- horizontal_data/cosn2 (:) [real,allocatable/public]
- horizontal_data/dtheta1a(:)[real,allocatable/public]
- horizontal_data/dpl0eq(:) [real,allocatable/public]
- horizontal_data/lmoddp (:) [logical,allocatable/public]
- horizontal_data/**d_1**(:) [real,allocatable/public]
- horizontal_data/wdplm(:,:) [real,allocatable/public]
- horizontal_data/dthetals(:)[real,allocatable/public]
- horizontal_data/n_theta_cal2ord(:) [integer, allocatable/public]
- horizontal_data/d_m(:) [real,allocatable/public]
- horizontal_data/sintheta(:)[real,allocatable/public]

Subroutines and functions

subroutine horizontal_data/horizontal()

Calculates functions of theta and phi, for exmample the Legendre functions, and functions of degree l and order m of the legendres.

```
Called from precalc()
Call to gauleg(), plm_theta(), init_fft()
subroutine horizontal_data/gauleg(sinthmin, sinthmax, theta_ord, gauss, n_th_max)
```

Subroutine is based on a NR code. Calculates N zeros of legendre polynomial P(l=N) in the interval [sinThMin,sinThMax]. Zeros are returned in radiants theta_ord(i) The respective weights for Gauss-integration are given in gauss(i).

Parameters

- **sinthmin** [real,in] :: lower bound in radiants
- **sinthmax** [real,in] :: upper bound in radiants
- **theta_ord** (n_th_max) [real,out] :: zeros cos(theta)
- gauss (n_th_max) [real,out] :: associated Gauss-Legendre weights
- **n_th_max** [integer,in] :: desired maximum degree

Called from horizontal()

10.6 Time stepping

10.6.1 step_time.f90

Quick access

Variables sigfile, dbdt_cmb_lmloc, dbdt_lmloc, dbdt_rloc, djdt_lmloc, djdt_rloc, dpdt_lmloc, dpdt_rloc, dsdt_lmloc, dsdt_rloc, dvprlm_lmloc, dvprlm_rloc, dvsrlm_rloc, dvsrlm_rloc, dvxbhlm_lmloc, dvxbhlm_rloc, dvxirlm_lmloc, dvxirlm_rloc, dvxvhlm_lmloc, dvxvhlm_rloc, dwdt_lmloc, dwdt_lmloc, dxidt_lmloc, dxidt_rloc, dzdt_lmloc, dzdt_rloc, dbdt_lmloc_container, dbdt_rloc_container, dflowdt_rloc_container, dsdt_lmloc_container, dxidt_lmloc_container, dxidt_lmloc_container, dxidt_rloc_container

Routines finalize_step_time(), initialize_step_time(), check_time_hits(),
 step_time()

Needed modules

- movie_data(t_movies())
- useful (abortrun(), l_correct_step(), logwrite()): library with several useful subroutines
- probe_mod
- lmloop_mod(lmloop())
- lmloop_data(llmmag(), lm_per_rank(), lm_on_last_rank(), ulm(), llm(), ulmmag())
- timing: Useful functions for time-stepping
- output_mod(output())
- radialloop(radialloopg())
- parallel_mod: This module contains the blocking information
- constants (zero(), half(), one()): module containing constants and parameters used in the code.
- num_param (tscale(), n_time_steps(), tend(), runtimelimit(), alpha(), dtmax(), dtmin(), runtime()): Module containing numerical and control parameters
- fieldslast: This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- logic (l_probe(), l_time_hits(), l_hel(), l_to(), l_dtrmagspec(), l_storetpot(), lverbose(), l_heat(), l_mag_lf(), l_perppar(), l_b_nl_icb(), l_abl(), l_tomovie(), l_double_curl(), l_mag(), l_dtbmovie(), l_htmovie(), l_storevpot(), l_runtimelimit(), l_fluxprofs(), l_storebpot(), l_viscbccalc(), l_conv(), l_pressgraph(), l_movie(), l_cmb_field(), l_true_time(), l_chemical_conv(), l_mag_kin(), l_ht(), l_power(), l_dt_cmb_field(), l_dtb(), l_save_out(), l_b_nl_cmb(), l_tp_form(), l_rms(), l_r_field()): Module containing the logicals that control the run
- precision_mod: This module controls the precision used in MagIC
- courant_mod(dt_courant())
- charmanip (dble2str(), capitalize()): This module contains several useful routines to manipule character strings
- blocking (nlmbs (), lmstartb (), lmstopb ()): Module containing blocking information
- nonlinear_bcs(get_b_nl_bcs())
- truncation (l_max(), lm_maxmag(), lmp_max(), l_maxmag(), n_r_max(), lm_max(), n_r_maxmag()): This module defines the grid points and the truncation
- mem_alloc(bytes_allocated(), memwrite()): This little module is used to estimate the global memory allocation used in MagIC

- $n_t_r field()$, $t_r st()$, $n_t_movie()$: This module contains the parameters for output control
- radial_data (n_r_cmb(), n_r_icb(), nrstopmag(), nrstartmag(), nrstop(), nrstart()): This module defines the MPI decomposition in the radial direction.
- communications (lo2r_field(), r2lo_redist_start(), lo2r_redist_wait(), r2lo_xi(), lm2r_type(), lo2r_xi(), r2lm_type(), lo2r_flow(), scatter_from_rank0_to_lo(), r2lo_flow(), r2lo_b(), r2lo_s(), get_global_sum(), lo2r_s(), r2lo_redist_wait())
- fields: This module contains the potential fields and their radial derivatives

Variables

- step_time_mod/dvxirlm_lmloc(:,:) [complex,private/pointer]
- step_time_mod/dzdt_lmloc(:,:) [complex,private/pointer]
- step_time_mod/dsdt_lmloc_container(:,:,:) [complex,private/target/allocatable]
- step_time_mod/**djdt_rloc**(:,:) [complex,private/pointer]
- step_time_mod/**dpdt_rloc** (:,:) [complex,private/pointer]
- step_time_mod/dsdt_rloc(:,:) [complex,private/pointer]
- step_time_mod/dbdt_lmloc_container(:,:,:) [complex,private/target/allocatable]
- step_time_mod/**dbdt_rloc_container** (:,:,:) [complex,private/target/allocatable]
- step_time_mod/dxidt_lmloc(:,:) [complex,private/pointer]
- step_time_mod/dflowdt_lmloc_container (:,:,:) [complex,private/target/allocatable]
- step_time_mod/dzdt_rloc(:,:) [complex,private/pointer]
- step_time_mod/dpdt_lmloc(:,:) [complex,private/pointer]
- step_time_mod/dwdt_lmloc(:,:) [complex,private/pointer]
- step_time_mod/dvsrlm_rloc(:,:) [complex,private/pointer]
- step_time_mod/dxidt_rloc_container(:,:,:) [complex,private/target/allocatable]
- step_time_mod/dxidt_rloc(:,:) [complex,private/pointer]
- step_time_mod/dvxbhlm_rloc(:,:) [complex,private/pointer]
- step time mod/dbdt lmloc(:,:) [complex,private/pointer]
- step_time_mod/sigfile [integer,private]
- step_time_mod/dvprlm_rloc(:,:) [complex,private/pointer]
- step_time_mod/dvsrlm_lmloc(:,:) [complex,private/pointer]
- step_time_mod/dvprlm_lmloc(:,:) [complex,private/pointer]
- step_time_mod/**dbdt_rloc**(:,:) [complex,private/pointer]
- step_time_mod/dwdt_rloc(:,:) [complex,private/pointer]
- step_time_mod/dvxvhlm_lmloc(:,:) [complex,private/pointer]
- step_time_mod/**dsdt_lmloc** (:,:) [complex,private/pointer]

- step_time_mod/dflowdt_rloc_container(:,;;) [complex,private/target/allocatable]
- step_time_mod/**dxidt_lmloc_container** (:,:,:) [complex,private/target/allocatable]
- step_time_mod/dvxvhlm_rloc(:,:) [complex,private/pointer]
- step_time_mod/dvxbhlm_lmloc(:,:) [complex,private/pointer]
- step_time_mod/dsdt_rloc_container (:,:,:) [complex,private/target/allocatable]
- step_time_mod/dvxirlm_rloc(:,:) [complex,private/pointer]
- step_time_mod/dbdt_cmb_lmloc(:) [complex,private/allocatable]
- step_time_mod/djdt_lmloc(:,:) [complex,private/pointer]

Subroutines and functions

This subroutine performs the actual time-stepping.

Parameters

- time [real,inout]
- **dt** [real,inout]
- dtnew [real,inout]
- **n_time_step** [integer,inout]

Called from magic

```
Call to walltime(), lo2r_redist_wait(), capitalize(), time2ms(),
    ms2time(), ltimelimit(), logwrite(), l_correct_step(), dble2str(),
    radialloopg(), lnegtime(), subtime(), addtime(), r2lo_redist_start(),
    r2lo_redist_wait(), scatter_from_rank0_to_lo(), output(),
    get_b_nl_bcs(), dt_courant(), check_time_hits(), abortrun(),
    lmloop(), meantime(), writetime()
```

subroutine step_time_mod/**check_time_hits**(*l_new_dt*, *time*, *dt*, *dt_new*)

Checks whether a certain dt is required to hit a specific output-time.

Parameters

- l_new_dt [logical,out] :: signfies change of dt!
- time [real,inout]
- **dt** [real,inout]
- **dt new** [real,inout]

Called from step_time()

10.6.2 courant.f90

Quick access

Routines dt courant(), courant()

Needed modules

- horizontal_data(osn2()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision_mod: This module controls the precision used in MagIC
- useful (logwrite()): library with several useful subroutines
- logic(l_cour_alf_damp(), l_mag(), l_mag_kin(), l_mag_lf()): Module containing the logicals that control the run
- radial_data(nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- parallel_mod: This module contains the blocking information
- num_param(delxh2(), delxr2(), courfac(), alffac()): Module containing numerical and control parameters
- physical_parameters (opm(), lffac()): Module containing the physical parameters
- truncation (nrp(), n_phi_max()): This module defines the grid points and the truncation
- blocking (nfs()): Module containing blocking information
- constants (one (), two (), half ()): module containing constants and parameters used in the code.
- radial_functions (or2(), or4(), orho1(), orho2()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

Subroutines and functions

subroutine courant_mod/**courant**(n_r , dtrkc, dthkc, vr, vt, vp, br, bt, bp, n_theta_min , n_theta_block)

Parameters

- **n_r** [integer,in] :: radial level
- **dtrkc** [real,inout] :: Courant step (based on radial advection)
- dthkc [real,inout] :: Courant step based on horizontal advection
- vr (nrp,nfs) [real,in] :: radial velocity
- vt (nrp,nfs) [real,in] :: longitudinal velocity
- **vp** (*nrp*,*nfs*) [*real*,*in*] :: azimuthal velocity

- **br** (*nrp*,*nfs*) [real,in] :: radial magnetic field
- **bt** (nrp,nfs) [real,in] :: longitudinal magnetic field
- **bp** (nrp,nfs) [real,in] :: azimuthal magnetic field
- n_theta_min [integer,in] :: first theta in block stored in fields
- n theta block [integer,in] :: size of theta block

```
subroutine courant_mod/dt_courant(dt_r, dt_h, l_new_dt, dt, dt_new, dtmax, dtrkc, dthkc)
```

Check if Courant criterion based on combined fluid and Alfven velocity is satisfied Returns new value of time step dtnew

dtr,dth: (output) radial/horizontal Courant time step n_time_step: (input) time step number l_new_dt: (output) flag indicating that time step is changed (=1) or not (=0) dt: (input) old time step dtnew: (output) new time step dtMin: (input) lower limit for time step (termination if dtnew < dtMin) dtMax: (input) upper limit for time step dtrkc: (input) radial Courant time step as function of radial level dthkc: (input) horizontal Courant time step as function of radial level

Parameters

- **dt r** [real,out]
- **dt h** [real,out]
- I new dt [logical,out]
- **dt** [real,in]
- dt_new [real,out]
- dtmax [real,in]
- dtrkc (nrstop-(nrstart)+1) [real,in]
- **dthkc** (*nrstop*-(*nrstart*)+1) [real,in]

Called from step_time()
Call to logwrite()

10.6.3 timing.f90

Description

Useful functions for time-stepping

Quick access

Needed modules

- precision_mod: This module controls the precision used in MagIC
- parallel_mod (rank ()): This module contains the blocking information
- mpimod: include "mpif.h"

Variables

- timing/msechour [integer,private/parameter=3600000]
- timing/msecsecond[integer,private/parameter=1000]
- timing/msecminute[integer,private/parameter=60000]

Subroutines and functions

```
subroutine timing/walltime(time)
```

This routine returns the wallclock time in four integer arguments.

```
Parameters time (4) [integer,out]
Called from step_time(), lmloop(), magic
Call to ms2time()
```

```
subroutine timing/ms2time(ms, time)
```

Transforms accumulated milliseconds ms into an four-element integer arrays time(4) containing the time in hours=time(1), minutes=time(2), seconds=time(3), and milliseconds=time(4).

Parameters

- ms [integer,in]
- time (4) [integer,out]

```
Called from subtime(), walltime(), step_time(), meantime(), addtime()
```

```
function timing/time2ms(time)
```

Transforms a four-element integer arrays time(4) containing the time in hours=time(1), minutes=time(2), seconds=time(3), and milliseconds=time(4) into accumulated milliseconds.

```
Parameters time (4) [integer,in]
Return time2ms [integer]
Called from subtime(), lnegtime(), step_time(), meantime(), addtime()
```

```
subroutine timing/subtime(timestart, timestop, timed)
```

Returns time passed between timeStop and timeStart. Note timeStop has to be younger than timeStart, otherwise 24 hours are added. This is necessary on systems like the IBM where the time counter as reset every day at midnight.

Parameters

```
• timestart (4) [integer,in]
                • timestop (4) [integer,in]
                • timed (4) [integer,out]
          Called from step_time(), lmloop()
          Call to time2ms(), ms2time()
function timing/ltimelimit(time, timemax)
          True when time exeeds timeMax
          Parameters
                • time (4) [integer,in]
                • timemax (4) [integer,in]
          Return ltimelimit [logical]
          Called from step_time()
subroutine timing/addtime(time1, time2)
          Parameters
                • time1 (4) [integer]
                • time2 (4) [integer]
          Called from step_time()
          Call to time2ms(), ms2time()
subroutine timing/meantime(time, n)
          Parameters
                • time (4) [integer]
                • n [integer,in]
          Called from step time()
          Call to time2ms(), ms2time()
function timing/lnegtime(time1, time2)
          Negative passed time? Means we have passed midnight. The wallclock time is reset to zero on some
          computers at midnight.
          Parameters
                • time1 (4) [integer,in]
                • time2 (4) [integer,in]
          Return Inegtime [logical]
          Called from step_time()
          Call to time2ms()
subroutine timing/writetime (nout, text, time)
```

242

Returns time passed between timeStop and timeStart. Note timeStop has to be younger than timeStart, otherwise 24 hours are added. This is necessary on systems like the IBM where the time counter are reset every day at midnight.

Parameters

- **nout** [integer,in]
- text [character,in]
- time (4) [integer,in]

Called from step_time(), lmloop(), magic

10.7 Linear calculation part of the time stepping (LMLoop)

10.7.1 LMLoop.f90

Quick access

Routines finalize_lmloop(), initialize_lmloop(), lmloop()

Needed modules

- debugging (debug_write())
- updatez_mod
- lmloop_data(ulmmag(), llmmag(), llm(), ulm())
- precision_mod: This module controls the precision used in MagIC
- updatewps_mod
- parallel_mod: This module contains the blocking information
- updatexi_mod
- updateb mod
- logic (l_anelastic_liquid(), l_chemical_conv(), lverbose(), l_heat(), l_single_matrix(), l_tp_form(), l_save_out(), l_mag(), l_conv()): Module containing the logicals that control the run
- updatewp_mod
- mem_alloc (memwrite(), bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- timing (writetime(), subtime(), walltime()): Useful functions for time-stepping
- blocking (lo_map(), lmstartb(), lmstopb()): Module containing blocking information
- updatewpt_mod
- truncation(lm_max(), l_max(), n_r_max(), n_r_maxmag()): This module defines the grid points and the truncation
- fieldslast: This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.

- omp_lib
- · updates mod
- output_data (n_log_file(), log_file()): This module contains the parameters for output control
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction
- communications (lo2r_field(), lo2r_xi(), lo2r_flow(), lo2r_s(), get_global_sum(), lo2r_redist_start())
- fields: This module contains the potential fields and their radial derivatives

Variables

Subroutines and functions

```
subroutine lmloop_mod/initialize_lmloop()
        Called from magic
        Call to initialize_updatewpt(),
                                                          initialize_updatewps(),
            initialize_updates(),
                                                            initialize_updatewp(),
            initialize_updatexi(), initialize_updatez(), initialize_updateb(),
            memwrite()
subroutine lmloop_mod/finalize_lmloop()
        Called from magic
        Call to finalize_updatewpt(), finalize_updatewps(), finalize_updates(),
            finalize_updatewp(), finalize_updatexi(), finalize_updatez(),
            finalize_updateb()
subroutine lmloop_mod/lmloop(w1, coex, time, dt, lmat, lrmsnext, lpressnext, dvxvhlm, dvxbhlm,
                                dvsrlm, dvprlm, dvxirlm, dsdt, dwdt, dzdt, dpdt, dxidt, dbdt,
                                djdt, lorentz_torque_ma, lorentz_torque_ic, b_nl_cmb, aj_nl_cmb,
                                aj_nl_icb
```

This subroutine performs the actual time-stepping.

Parameters

- **w1** [real,in]
- coex [real,in]
- time [real,in]
- **dt** [real,in]
- lmat [logical,in]
- **Irmsnext** [logical,in]
- **lpressnext** [logical,in]
- **dvxvhlm** (*ulm*-(*llm*)+1,*n_r_max*) [complex,inout]
- **dvxbhlm** (*ulmmag-*(*llmmag*)+1,*n_r_maxmag*) [*complex*,*inout*]
- **dvsrlm** (*ulm*-(*llm*)+1,*n_r_max*) [complex,inout]

```
• dvprlm (ulm-(llm)+1,n_r_max) [complex,inout]
      • dvxirlm (ulm-(llm)+1,n_r_max) [complex,inout]
      • dsdt (ulm-(llm)+1,n_r_max) [complex,inout]
      • dwdt (ulm-(llm)+1,n_r_max) [complex, inout]
      • dzdt (ulm-(llm)+1,n_r_max) [complex,in]
      • dpdt (ulm-(llm)+1, n r max) [complex,in]
     • dxidt (ulm-(llm)+1,n_r_max) [complex,inout]
      • dbdt (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
      • djdt (ulmmag-(llmmag)+1,n_r_maxmag) [complex,inout]
      • lorentz_torque_ma [real,in]
      • lorentz_torque_ic [real,in]
      • b_nl_cmb (lm_max) [complex,in] :: nonlinear bc for b at CMB
      • aj_nl_cmb (lm_max) [complex,in] :: nonlinear bc for aj at CMB
      • aj_nl_icb (lm_max) [complex,in] :: nonlinear bc for dr aj at ICB
Called from step time()
Call to walltime(), updates ala(), updates(), lo2r redist start(),
```

updatexi(), updatewpt(), updatewps(), updatewp(), updateb(),

10.7.2 updateWPS.f90

subtime(), writetime()

Quick access

Needed modules

- horizontal_data (hdif_s(), dlh(), hdif_v()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- rms (difpol2hint(), dtvpol1mr(), dtvpol2hint(), difpol1mr()): This module contains the calculation of thr RMS force balance and induction terms.
- useful (abortrun ()): library with several useful subroutines
- lmloop_data(llm(), ulm())
- init_fields (bots (), tops ()): This module is used to construct the initial solution.
- radial_der(get_dr(), get_ddr(), get_dddr()): Radial derivatives functions
- parallel_mod (chunksize(), rank()): This module contains the blocking information
- num_param(alpha()): Module containing numerical and control parameters

- physical_parameters (kbotv(), buofac(), kbots(), opr(), vischeatfac(), ktopv(), ra(), ktops(), thexpnb(), corfac(), ktopp()): Module containing the physical parameters
- omp_lib
- radial_functions (rscheme_oc(), kappa(), temp0(), dlkappa(), dltemp0(), dlvisc(), dlalpha0(), rho0(), or2(), ddltemp0(), or1(), visc(), beta(), r(), dentropy0(), rgrav(), alpha0(), ogrun(), ddlalpha0(), dbeta(), orho1()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- algebra (prepare_mat(), solve_mat())
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- rms_helpers (hint2pol()): This module contains several useful subroutines required to compute RMS diagnostics
- blocking (lo_sub_map(), lmstartb(), nlmbs(), lmstopb(), lo_map(), st_map(), st_sub_map()): Module containing blocking information
- constants (osq4pi(), pi(), third(), three(), two(), four(), zero(), half(), one()): module containing constants and parameters used in the code.
- truncation (lm_max(), l_max(), n_r_max()): This module defines the grid points and the truncation
- precision_mod: This module controls the precision used in MagIC
- fields (work_lmloc()): This module contains the potential fields and their radial derivatives
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- communications (get_global_sum())
- logic (l_update_v(), l_rms(), l_temperature_diff()): Module containing the logicals that control the run

Variables

- updatewps_mod/**pre**(:) [complex,private/allocatable]
- updatewps_mod/ps0pivot (:) [integer,private/allocatable]
- updatewps_mod/**ps0mat_fac**(:,:) [real,private/allocatable]
- updatewps_mod/lwpsmat(:)[logical,allocatable/public]
- updatewps_mod/ps0mat(:,:) [real,private/allocatable]
- updatewps_mod/buo(:) [complex,private/allocatable]
- updatewps_mod/cor00_fac [real,private]
- updatewps_mod/wpsmat (:,:,:) [real,private/allocatable]
- updatewps_mod/wpspivot(:,:) [integer,private/allocatable]
- updatewps_mod/maxthreads[integer,private]
- updatewps_mod/workb(:,:) [complex,private/allocatable]
- updatewps_mod/workc(:,:) [complex,private/allocatable]
- updatewps_mod/workd(:,:) [complex,private/allocatable]

- updatewps_mod/**rhs1**(:,:,:) [complex,private/allocatable]
- updatewps_mod/wpsmat_fac(:,:,:) [real,private/allocatable]
- updatewps_mod/dif(:)[complex,private/allocatable]
- updatewps_mod/dtv(:) [complex,private/allocatable]

Subroutines and functions

Parameters

time derivatives of w and p

- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,inout]
- dw (ulm-(llm)+1,n_r_max) [complex,inout]
- **ddw** (*ulm*-(*llm*)+1,*n_r_max*) [complex,out]
- **z10** (*n*_*r*_*max*) [real,in]
- **dwdt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **dwdtlast** (*ulm*-(*llm*)+1,*n_r_max*) [complex,inout]
- **p** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*inout*]
- **dp** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*, *out*]
- **dpdt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **dpdtlast** (*ulm*-(*llm*)+1,*n_r_max*) [complex,inout]
- **s** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,inout]
- ds (ulm-(llm)+1, n_r_max) [complex,inout]
- **dvsrlm** (*ulm*-(*llm*)+1,*n_r_max*) [complex,inout]
- **dsdt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*inout*]
- **dsdtlast** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*inout*]
- w1 [real,in] :: weight for time step!
- coex [real,in] :: factor depending on alpha
- **dt** [real,in] :: time step
- **nlmb** [integer,in] :: block number
- **lrmsnext** [logical,in]

Called from lmloop()

```
Call to get_ps0mat(), get_wpsmat(), get_dddr(), get_ddr(), hint2pol()
```

subroutine updatewps_mod/get_wpsmat(dt, l, hdif_vel, hdif_s, wpsmat, wpspivot, wpsmat_fac)

Purpose of this subroutine is to contruct the time step matrix wpmat for the NS equation.

Parameters

- **dt** [real,in]
- l [integer,in]
- hdif_vel [real,in]
- hdif_s [real,in]
- **wpsmat** (3**n_r_max*,3**n_r_max*) [real,out]
- wpspivot (3*n_r_max) [integer,out]
- wpsmat_fac (3*n_r_max,2) [real,out]

Called from updatewps()

Call to prepare_mat(), abortrun()

subroutine updatewps_mod/get_ps0mat (dt, psmat, pspivot, psmat_fac)

Parameters

- **dt** [real,in]
- **psmat** (2**n_r_max*,2**n_r_max*) [real,out]
- **pspivot** (2**n_r_max*) [integer,out]
- **psmat_fac** (2**n_r_max*,2) [real,out]

Called from updatewps()

Call to prepare_mat(), abortrun()

10.7.3 updateWPT.f90

Quick access

```
Variables cor00_fac, pt0pivot, wptpivot, lwptmat, buo, pre, pt0mat, pt0mat_fac, workc, workd, wptmat, wptmat_fac
```

```
Routines finalize_updatewpt(), initialize_updatewpt(), get_wptmat(), get_pt0mat(), updatewpt()
```

Needed modules

- horizontal_data (hdif_s(), dlh(), hdif_v()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- rms (difpol2hint(), dtvpol1mr(), dtvpol2hint(), difpol1mr()): This module contains the calculation of thr RMS force balance and induction terms.
- useful (abortrun()): library with several useful subroutines

- lmloop_data(llm(), ulm())
- init_fields (bots (), tops ()): This module is used to construct the initial solution.
- radial_der(get_dr(), get_ddr(), get_dddr()): Radial derivatives functions
- parallel_mod (chunksize(), rank()): This module contains the blocking information
- num_param(alpha()): Module containing numerical and control parameters
- physical_parameters (kbotv(), buofac(), kbots(), opr(), vischeatfac(), ktopv(), ra(), ktops(), thexpnb(), corfac(), ktopp()): Module containing the physical parameters
- omp_lib
- radial_functions (rho0(), or2(), or1(), ogrun(), temp0(), dentropy0(), otemp1(), rscheme_oc(), dlkappa(), rgrav(), orho1(), orho2(), dlvisc(), ddltemp0(), dltemp0(), beta(), alpha0(), kappa(), visc(), dlalpha0(), dbeta(), r(), ddlalpha0()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- algebra (prepare_mat(), solve_mat())
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- rms_helpers (hint2pol()): This module contains several useful subroutines required to compute RMS diagnostics
- blocking (lo_sub_map(), lmstartb(), nlmbs(), lmstopb(), lo_map(), st_map(), st_sub_map()): Module containing blocking information
- constants (osq4pi(), pi(), third(), three(), two(), four(), zero(), half(), one()): module containing constants and parameters used in the code.
- truncation (lm_max(), l_max(), n_r_max()): This module defines the grid points and the truncation
- precision_mod: This module controls the precision used in MagIC
- fields (work_lmloc()): This module contains the potential fields and their radial derivatives
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- communications (get_global_sum())
- logic (l_update_v(), l_rms(), l_temperature_diff()): Module containing the logicals that control the run

Variables

- updatewpt_mod/pre (:) [complex,private/allocatable]
- updatewpt_mod/workc(:,:) [complex,private/allocatable]
- updatewpt_mod/wptmat_fac(:,:,:) [real,private/allocatable]
- updatewpt_mod/workd(:,:) [complex,private/allocatable]
- updatewpt_mod/lwptmat (:) [logical,allocatable/public]
- updatewpt_mod/maxthreads [integer,private]
- updatewpt_mod/**buo**(:) [complex,private/allocatable]
- updatewpt_mod/cor00_fac [real,private]

- updatewpt_mod/pt0mat_fac(:,:) [real,private/allocatable]
- updatewpt_mod/wptpivot (:,:) [integer,private/allocatable]
- updatewpt_mod/workb(:,:) [complex,private/allocatable]
- updatewpt_mod/pt0mat(:,:) [real,private/allocatable]
- updatewpt_mod/rhs1(:,:,:) [complex,private/allocatable]
- updatewpt_mod/wptmat (:,:,:) [real,private/allocatable]
- updatewpt_mod/**pt0pivot** (:) [integer,private/allocatable]
- updatewpt_mod/dif(:) [complex,private/allocatable]
- updatewpt_mod/dtv(:) [complex,private/allocatable]

Subroutines and functions

snext)

updates the poloidal velocity potential w, the pressure p, and their derivatives adds explicit part to time derivatives of w and p

- w (ulm-(llm)+1,n_r_max) [complex,inout]
- dw (ulm-(llm)+1,n r max) [complex,inout]
- **ddw** (*ulm*-(*llm*)+1,*n_r_max*) [complex,out]
- **z10** (*n*_*r*_*max*) [real,in]
- **dwdt** (*ulm*-(*llm*)+1,*n_r_max*) [*complex*,*in*]
- **dwdtlast** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,inout]
- **p** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,inout]
- **dp** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*, *out*]
- **dpdt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **dpdtlast** (ulm-(llm)+1,n_r_max) [complex,inout]
- **tt** (*ulm*-(*llm*)+1,*n_r_max*) [complex,inout]
- **dtt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,inout]
- **dvtrlm** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,inout]
- **dvprlm** (*ulm*-(*llm*)+1,*n_r_max*) [complex,inout]
- **dttdt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*inout*]
- **dttdtlast** (*ulm*-(*llm*)+1,*n_r_max*) [complex,inout]

```
• w1 [real,in] :: weight for time step!
               • coex [real,in] :: factor depending on alpha
               • dt [real,in] :: time step
               • nlmb [integer,in] :: block number
               • Irmsnext [logical,in]
         Called from lmloop()
         Call to get_pt0mat(), get_wptmat(), get_dddr(), get_ddr(), hint2pol()
subroutine updatewpt_mod/get_wptmat (dt, l, hdif_vel, hdif_t, wptmat, wptpivot, wptmat_fac)
         Purpose of this subroutine is to contruct the time step matrix wpmat for the NS equation.
         Parameters
               • dt [real,in]
               • 1 [integer,in]
               • hdif vel [real,in]
               • hdif_t [real,in]
               • wptmat (3*n_r_max,3*n_r_max) [real,out]
               • wptpivot (3*n_r_max) [integer,out]
               • wptmat_fac (3*n_r_max,2) [real,out]
         Called from updatewpt()
         Call to prepare_mat(), abortrun()
subroutine updatewpt_mod/get_pt0mat (dt, ptmat, ptpivot, ptmat_fac)
         Parameters
               • dt [real,in]
               • ptmat (2*n_r_max,2*n_r_max) [real,out]
               • ptpivot (2*n_r_max) [integer,out]
               • ptmat_fac (2*n_r_max,2) [real,out]
         Called from updatewpt()
         Call to prepare_mat(), abortrun()
10.7.4 updateWP.f90
Quick access
     Variables p0pivot, wppivot, lwpmat, work, ddddw, dwold, p0mat, wpmat, wpmat_fac
     Routines finalize_updatewp(),
                                           get_wpmat(), get_p0mat(), updatewp()
```

Needed modules

- horizontal_data(dlh(), hdif_v()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- rms (difpol2hint(), dtvpol1mr(), dtvpol2hint(), difpol1mr()): This module contains the calculation of thr RMS force balance and induction terms.
- useful (abortrun ()): library with several useful subroutines
- lmloop_data(llm(), ulm())
- radial_der (get_dr(), get_ddr(), get_dddr()): Radial derivatives functions
- integration (rint_r()): Radial integration functions
- parallel_mod (chunksize ()): This module contains the blocking information
- num_param(alpha()): Module containing numerical and control parameters
- physical_parameters (kbotv(), buofac(), vischeatfac(), ktopv(), chemfac(), ra(), thexpnb(), ktopp()): Module containing the physical parameters
- omp_lib
- radial_functions(alpha0(), orho1(), ddlvisc(), rho0(), or2(), rscheme_oc(), or1(), ddbeta(), visc(), beta(), dlvisc(), temp0(), rgrav(), ogrun(), r(), dbeta()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- algebra (prepare_mat(), solve_mat())
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- rms_helpers (hint2pol()): This module contains several useful subroutines required to compute RMS diagnostics
- blocking (lo_sub_map(), lmstartb(), nlmbs(), lmstopb(), lo_map(), st_map(), st_sub_map()): Module containing blocking information
- constants (third(), three(), two(), four(), zero(), half(), one()): module containing constants and parameters used in the code.
- truncation (lm_max(), l_max(), n_r_max()): This module defines the grid points and the truncation
- precision_mod: This module controls the precision used in MagIC
- fields (work_lmloc()): This module contains the potential fields and their radial derivatives
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- communications (get_global_sum())
- logic(l_double_curl(), l_update_v(), l_rms(), l_chemical_conv(), l_fluxprofs()): Module containing the logicals that control the run

Variables

- updatewp_mod/**pre**(:) [complex,private/allocatable]
- updatewp_mod/**ddddw** (:,:) [complex,private/allocatable]
- updatewp_mod/maxthreads [integer,private]

- updatewp_mod/buo(:) [complex,private/allocatable]
- updatewp_mod/lwpmat (:) [logical,allocatable/public]
- updatewp_mod/wpmat_fac (:,:,:) [real,private/allocatable]
- updatewp_mod/p0mat(:,:) [real,private/allocatable]
- updatewp_mod/dwold(:,:) [complex,private/allocatable]
- updatewp_mod/workb (:,:) [complex,private/allocatable]
- updatewp_mod/work (:) [real,private/allocatable]
- updatewp_mod/**rhs1** (:,:,:) [complex,private/allocatable]
- updatewp_mod/wppivot (:,:) [integer,private/allocatable]
- updatewp_mod/wpmat(:,:,:) [real,private/allocatable]
- updatewp_mod/dif(:)[complex,private/allocatable]
- updatewp_mod/p0pivot (:) [integer,private/allocatable]
- updatewp_mod/dtv(:) [complex,private/allocatable]

Subroutines and functions

subroutine updatewp_mod/**updatewp**(w, dw, ddw, dvxvhlm, dwdt, dwdtlast, p, dp, dpdt, dpdtlast, s, xi, w1, coex, dt, nlmb, lrmsnext, lpressnext)

updates the poloidal velocity potential w, the pressure p, and their derivatives adds explicit part to time derivatives of w and p

- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,inout]
- dw (ulm-(llm)+1,n r max) [complex,inout]
- **ddw** (ulm-(llm)+1,n_r_max) [complex,inout]
- **dvxvhlm** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*inout*]
- **dwdt** (*ulm*-(*llm*)+1,*n_r_max*) [*complex*,*inout*]
- **dwdtlast** (*ulm*-(*llm*)+1,*n_r_max*) [complex,inout]
- **p** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*inout*]
- **dp** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*, *out*]
- **dpdt** $(ulm-(llm)+1,n_r_max)$ [complex,in]
- **dpdtlast** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*inout*]
- **s** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **xi** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]

```
• w1 [real,in] :: weight for time step!
                • coex [real,in] :: factor depending on alpha
                • dt [real,in] :: time step
                • nlmb [integer,in] :: block number
                • Irmsnext [logical,in]
                • lpressnext [logical,in]
          Called from lmloop()
          Call to get_p0mat(), get_wmat(), get_wpmat(), rint_r(), get_ddr(),
               get dddr(), hint2pol()
subroutine updatewp_mod/get_wpmat (dt, l, hdif, wpmat, wppivot, wpmat_fac)
          Purpose of this subroutine is to contruct the time step matrix wpmat for the NS equation.
          Parameters
                • dt [real,in]
                • l [integer,in]
                • hdif [real,in]
                • wpmat (2*n_r_max,2*n_r_max) [real,out]
                • wppivot (2*n_r_max) [integer,out]
                • wpmat_fac (2*n_r_max,2) [real,out]
          Called from updatewp()
          Call to prepare_mat(), abortrun()
subroutine updatewp_mod/get_wmat (dt, l, hdif, wmat, wpivot, wmat_fac)
          Purpose of this subroutine is to contruct the time step matrix wpmat for the NS equation. This matrix
          corresponds here to the radial component of the double-curl of the Navier-Stokes equation.
          Parameters
                • dt [real,in]
```

- I [integer,in]
- hdif [real,in]
- wmat (2*n_r_max,2*n_r_max) [real,out]
- wpivot (2*n_r_max) [integer,out]
- wmat_fac (2*n_r_max,2) [real,out]

Called from updatewp()

Call to prepare_mat(), abortrun()

subroutine updatewp_mod/get_p0mat (pmat, ppivot)

Parameters

• **pmat** (*n_r_max*,*n_r_max*) [real,out]

```
• ppivot (n_r_max) [integer,out]
```

```
Called from updatewp()
```

Call to prepare_mat(), abortrun()

10.7.5 updateZ.f90

Quick access

```
Variables maxthreads, 1z10mat, z10pivot, zpivot, 1zmat, dif, dtv, z10mat_fac, workb, z10mat, zmat_fac, rhs1, zmat
```

- horizontal_data(dlh(), hdif_v()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- rms (dtvtor2hint (), diftor2hint ()): This module contains the calculation of thr RMS force balance and induction terms.
- useful (abortrun ()): library with several useful subroutines
- lmloop_data(llm(), ulm())
- *init fields*: This module is used to construct the initial solution.
- radial_der (get_ddr ()): Radial derivatives functions
- precision_mod: This module controls the precision used in MagIC
- special: This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- truncation (lm_max(), l_max(), n_r_max()): This module defines the grid points and the truncation
- parallel_mod: This module contains the blocking information
- num_param (alpha(), amstart()): Module containing numerical and control parameters
- physical_parameters (po_diff(), kbotv(), lffac(), diff_prec_angle(), oek(), ktopv(), prec_angle(), po()): Module containing the physical parameters
- omp_lib
- algebra (prepare_mat(), solve_mat())
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- rms_helpers (hint2tor()): This module contains several useful subroutines required to compute RMS diagnostics
- blocking (lo_sub_map(), lmstartb(), nlmbs(), lmstopb(), lo_map(), st_map(), st_sub_map()): Module containing blocking information

- constants (c_moi_oc(), y11_norm(), pi(), third(), y10_norm(), c_z10_omega_ma(), c_lorentz_ic(), c_dt_z10_ic(), one(), four(), c_moi_ma(), zero(), c_z10_omega_ic(), two(), c_moi_ic(), c_dt_z10_ma(), c_lorentz_ma()): module containing constants and parameters used in the code.
- radial_functions (rscheme_oc(), r_cmb(), rho0(), or2(), or1(), visc(), beta(), dlvisc(), r_icb(), r(), dbeta()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- torsional_oscillations (ddzasl()): This module contains information for TO calculation and output
- outrot (get_angular_moment())
- fields (work_lmloc()): This module contains the potential fields and their radial derivatives
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- communications(get_global_sum())
- logic (l_rot_ic(), l_diff_prec(), l_precession(), l_correct_amz(), l_correct_ame(), l_update_v(), l_srma(), l_z10mat(), l_rot_ma(), l_to(), l_sric(), l_rms()): Module containing the logicals that control the run

Variables

- updatez mod/lz10mat [logical, public]
- updatez_mod/zmat_fac(:,:) [real,private/allocatable]
- updatez_mod/zmat(:,:,:) [real,private/allocatable]
- updatez_mod/**z10mat_fac**(:) [real,private/allocatable]
- updatez_mod/lzmat(:) [logical,allocatable/public]
- updatez_mod/maxthreads [integer,private]
- updatez_mod/workb (:,:) [complex,private/allocatable]
- updatez_mod/**rhs1** (:,:,:) [complex,private/allocatable]
- updatez_mod/**z10mat** (:,:) [real,private/allocatable]
- updatez_mod/dif(:)[complex,private/allocatable]
- updatez mod/**z10pivot** (:) [integer, private/allocatable]
- updatez_mod/**zpivot** (:,:) [integer,private/allocatable]
- updatez_mod/dtv(:) [complex,private/allocatable]

Subroutines and functions

```
subroutine updatez_mod/updatez(z, dz, dzdt, dzdtlast, time, omega_ma, d_omega_ma_dtlast, omega_ic, d_omega_ic_dtlast, lorentz_torque_ma, lorentz_torque_malast, lorentz_torque_ic, lorentz_torque_iclast, w1, coex, dt, lrmsnext)
```

updates the toroidal potential z and its radial derivatives adds explicit part to time derivatives of z

Parameters

- \mathbf{z} (ulm-(llm)+1,n r max) [complex,inout]
- **dz** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*, *out*]
- **dzdt** (*ulm*-(*llm*)+1,*n_r_max*) [*complex*,*in*]
- **dzdtlast** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*inout*]
- **time** [real,in] :: Current time
- omega_ma [real,out] :: Calculated OC rotation
- d_omega_ma_dtlast [real,inout] :: Time derivative of OC rotation of previous step
- omega_ic [real,out] :: Calculated IC rotation
- **d_omega_ic_dtlast** [real,inout] :: Time derivative of IC rotation of previous step
- lorentz_torque_ma [real,in] :: Lorentz torque (for OC rotation)
- lorentz_torque_malast [real,in] :: Lorentz torque (for OC rotation) of previous step
- **lorentz_torque_ic** [real,in] :: Lorentz torque (for IC rotation)
- lorentz_torque_iclast [real,in] :: Lorentz torque (for IC rotation) of previous step
- w1 [real,in] :: Weight for time step
- coex [real,in] :: Factor depending on alpha
- **dt** [real,in] :: Time step interval
- **Irmsnext** [logical,in] :: Logical for storing update if (l_RMS.and.l_logNext)

```
Call to get_zmat(), get_z10mat(), get_ddr(), get_angular_moment(),
    hint2tor()
```

```
subroutine updatez_mod/get_z10mat(dt, l, hdif, zmat, zpivot, zmat_fac)
```

Purpose of this subroutine is to construct and LU-decompose the inversion matrix z10mat for the implicit time step of the toroidal velocity potential z of degree l=1 and order m=0. This differs from the the normal zmat only if either the ICB or CMB have no-slip boundary condition and inner core or mantle are chosen to rotate freely (either kbotv=1 and/or ktopv=1).

Parameters

- **dt** [real,in] :: Time step internal
- 1 [integer,in] :: Variable to loop over l's
- hdif [real,in] :: Value of hyperdiffusivity in zMat terms
- **zmat** (n_r_max,n_r_max) [real,out] :: LHS matrix to calculate z
- **zpivot** (*n_r_max*) [integer,out] :: Pivot to invert zMat
- **zmat_fac** (*n_r_max*) [real,out] :: Inverse of max(zMat) for inversion

Called from updatez()

```
Call to prepare_mat(), abortrun()
```

```
subroutine updatez_mod/get_zmat (dt, l, hdif, zmat, zpivot, zmat_fac)
```

Purpose of this subroutine is to contruct the time step matricies zmat(i,j) for the NS equation.

Parameters

- **dt** [real,in] :: Time interval
- I [integer,in] :: Variable to loop over degrees
- **hdif** [real,in] :: Hyperdiffusivity
- **zmat** (*n_r_max*,*n_r_max*) [real,out] :: Matrix with LHS of z equation
- **zpivot** (*n_r_max*) [integer,out] :: Pivot for zMat inversion
- **zmat_fac** (*n_r_max*) [real,out] :: Inverse of max(zMat) for the inversion

```
Called from updatez()
```

Call to prepare_mat(), abortrun()

10.7.6 updateS.f90

Quick access

- horizontal_data(hdif_s(), dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- truncation (lm_max(), l_max(), n_r_max()): This module defines the grid points and the truncation
- useful (abortrun()): library with several useful subroutines
- algebra (prepare_mat(), solve_mat())
- fields (work lmloc()): This module contains the potential fields and their radial derivatives
- logic(l_anelastic_liquid(), l_update_s()): Module containing the logicals that control the run
- lmloop_data(llm(), ulm())
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- precision_mod: This module controls the precision used in MagIC
- init_fields (bots (), tops ()): This module is used to construct the initial solution.
- parallel_mod (chunksize(), rank()): This module contains the blocking information
- num_param (alpha()): Module containing numerical and control parameters

- radial_der (get_dr(), get_ddr()): Radial derivatives functions
- physical_parameters (kbots(), ktops(), opr()): Module containing the physical parameters
- omp_lib
- blocking (lo_sub_map(), lmstartb(), nlmbs(), lmstopb(), lo_map(), st_map()): Module containing blocking information
- constants (zero(), two(), one()): module containing constants and parameters used in the code.
- radial_functions (rscheme_oc(), orhol(), dlkappa(), or2(), orl(), dltemp0(), beta(), temp0(), dentropy0(), kappa()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

- updates_mod/maxthreads [integer,private]
- updates_mod/**spivot** (:,:) [integer,private/allocatable]
- updates_mod/smat(:,:,:) [real,private/allocatable]
- updates_mod/smat_fac(:,:) [real,private/allocatable]
- updates_mod/**rhs1** (:,:,:) [complex,private/allocatable]
- updates mod/s0mat fac(:) [real,private/allocatable]
- updates mod/s0mat(:,:) [real,private/allocatable]
- updates_mod/lsmat(:)[logical,allocatable/public]
- updates_mod/s0pivot (:) [integer,private/allocatable]

Subroutines and functions

- **s** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,inout]
- $ds (ulm-(llm)+1,n_r_max) [complex,out]$
- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **dvsrlm** (*ulm*-(*llm*)+1,*n_r_max*) [*complex*,*inout*]
- **dsdt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,inout]
- **dsdtlast** (*ulm*-(*llm*)+1,*n_r_max*) [complex,inout]
- w1 [real,in] :: weight for time step!

```
• coex [real,in] :: factor depending on alpha
                 • dt [real,in] :: time step
                 • nlmb [integer,in]
           Called from lmloop()
           Call to get_s0mat(), get_smat(), get_ddr()
subroutine updates_mod/updates_ala(s, ds, w, dvsrlm, dsdt, dsdtlast, w1, coex, dt, nlmb)
           updates the entropy field s and its radial derivatives adds explicit part to time derivatives of s
           Parameters
                 • \mathbf{s} (ulm-(llm)+1,n_r_max) [complex,inout]
                 • ds (ulm-(llm)+1,n_r_max) [complex, out]
                 • w (ulm-(llm)+1,n_r_max) [complex,in]
                 • dvsrlm (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dsdt (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dsdtlast (ulm-(llm)+1,n_r_max) [complex,inout]
                 • w1 [real,in] :: weight for time step!
                 • coex [real,in] :: factor depending on alpha
                 • dt [real,in] :: time step
                 • nlmb [integer,in]
           Called from lmloop()
           Call to get_s0mat(), get_smat(), get_ddr()
subroutine updates_mod/get_s0mat(dt, smat, spivot, smat_fac)
           Purpose of this subroutine is to contruct the time step matrix sMat0
           Parameters
                 • dt [real,in]
                 • smat (n_r_max,n_r_max) [real,out]
```

• **spivot** (*n r max*) [integer,out]

• smat_fac (n_r_max) [real,out]

Called from updates(), updates_ala()

Call to prepare_mat(), abortrun()

subroutine updates_mod/get_smat(dt, l, hdif, smat, spivot, smat_fac)

Purpose of this subroutine is to contruct the time step matricies sMat(i,j) and s0mat for the entropy equation.

Parameters

• dt [real,in]

```
• I [integer,in]
```

- hdif [real,in]
- **smat** (*n_r_max*,*n_r_max*) [*real*,*out*]
- **spivot** (*n_r_max*) [integer,out]
- smat fac (n r max) [real,out]

Called from updates(), updates ala()

Call to prepare_mat(), abortrun()

10.7.7 updateXI.f90

Quick access

- horizontal_data (hdif_xi(), dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel_mod (chunksize(), rank()): This module contains the blocking information
- truncation (lm_max(), l_max(), n_r_max()): This module defines the grid points and the truncation
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (abortrun ()): library with several useful subroutines
- algebra (prepare_mat(), solve_mat())
- fields (work_lmloc()): This module contains the potential fields and their radial derivatives
- logic (l_update_xi()): Module containing the logicals that control the run
- lmloop_data(llm(), ulm())
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- precision mod: This module controls the precision used in MagIC
- init_fields (botxi(), topxi()): This module is used to construct the initial solution.
- num_param(alpha()): Module containing numerical and control parameters
- radial_der (get_dr(), get_ddr()): Radial derivatives functions
- physical_parameters (kbotxi(), osc(), ktopxi()): Module containing the physical parameters
- omp_lib
- blocking (lo_sub_map(), lmstartb(), nlmbs(), lmstopb(), lo_map(), st_map()): Module containing blocking information
- constants (zero(), two(), one()): module containing constants and parameters used in the code.

• radial_functions (or2(), beta(), orho1(), rscheme_oc(), or1()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

```
• updatexi mod/maxthreads [integer, private]
```

- updatexi mod/xipivot(:,:) [integer, private/allocatable]
- updatexi_mod/xi0mat(:,:) [real,private/allocatable]
- updatexi_mod/**rhs1** (:,:,:) [complex,private/allocatable]
- updatexi_mod/ximat(:,:,:) [real,private/allocatable]
- updatexi_mod/xi0pivot(:)[integer,private/allocatable]
- updatexi_mod/ximat_fac(:,:) [real,private/allocatable]
- updatexi_mod/xi0mat_fac(:) [real,private/allocatable]
- updatexi_mod/lximat (:) [logical,allocatable/public]

Subroutines and functions

```
subroutine updatexi_mod/finalize_updatexi()
          Called from finalize_lmloop()
subroutine updatexi_mod/updatexi(xi, dxi, dvxirlm, dxidt, dxidtlast, w1, coex, dt, nlmb)
          updates the entropy field s and its radial derivatives adds explicit part to time derivatives of s
          Parameters
                 • xi (ulm-(llm)+1,n r max) [complex,inout]
                • dxi (ulm-(llm)+1,n_r_max) [complex,out]
                 • dvxirlm (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dxidt (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dxidtlast (ulm-(llm)+1,n_r_max) [complex, inout]
                 • w1 [real,in] :: weight for time step!
                 • coex [real,in] :: factor depending on alpha
                 • dt [real,in] :: time step
                 • nlmb [integer,in]
          Called from lmloop()
          Call to get_xi0mat(), get_ximat(), get_ddr()
```

subroutine updatexi_mod/get_xi0mat(dt, ximat, xipivot, ximat_fac)

Purpose of this subroutine is to contruct the time step matrix xiMat0

Chapter 10. Description of the Fortran modules

Parameters

- **dt** [real,in]
- ximat (n_r_max,n_r_max) [real,out]
- **xipivot** (*n_r_max*) [integer,out]
- ximat_fac (n_r_max) [real,out]

Called from updatexi()

Call to prepare_mat(), abortrun()

subroutine updatexi_mod/get_ximat (dt, l, hdif, ximat, xipivot, ximat_fac)

Purpose of this subroutine is to contruct the time step matricies xiMat(i,j) for the equation for the chemical composition.

Parameters

- **dt** [real,in]
- I [integer,in]
- hdif [real,in]
- **ximat** (*n_r_max*,*n_r_max*) [*real*,*out*]
- **xipivot** (*n_r_max*) [integer,out]
- ximat fac (n r max) [real,out]

Called from updatexi()

Call to prepare_mat(), abortrun()

10.7.8 updateB.f90

Quick access

```
Variables bpivot, jpivot, lbmat, dtp, dtt, bmat_fac, jmat_fac, bmat, jmat, rhs2

Routines finalize_updateb(), initialize_updateb(), updateb(), get_bmat()
```

- horizontal_data (hdif_b(), dphi(), dlh(), d_l(), d_lp1()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- rms (dtbtor2hint(), dtbpollmr(), dtbpol2hint()): This module contains the calculation of thr RMS force balance and induction terms.
- useful (abortrun ()): library with several useful subroutines
- lmloop_data(llmmag(), ulmmag())
- init_fields (bpeakbot (), bpeaktop ()): This module is used to construct the initial solution.
- radial_der_even(get_ddr_even())
- radial_der(get_dr(), get_ddr()): Radial derivatives functions

- special: This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- parallel_mod (chunksize(), rank()): This module contains the blocking information
- num_param(alpha()): Module containing numerical and control parameters
- physical_parameters (sigma_ratio(), ktopb(), tmagcon(), imagcon(), o_sr(), n_r_lcr(), opm(), conductance_ma(), kbotb()): Module containing the physical parameters
- omp_lib
- radial_functions (d2cheb_ic(), rscheme_oc(), dcheb_ic(), r_cmb(), cheb_norm_ic(), or2(), dr_fac_ic(), or1(), dllambda(), r(), o_r_ic(), chebt_ic_even(), chebt_ic(), cheb_ic(), lambda()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- algebra (prepare_mat(), solve_mat())
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- rms_helpers (hint2torlm(), hint2pollm()): This module contains several useful subroutines required to compute RMS diagnostics
- blocking (lo_sub_map(), lmstartb(), nlmbs(), lmstopb(), lo_map(), st_map(), st_sub_map()): Module containing blocking information
- constants (one (), three (), two (), zero (), half (), pi ()): module containing constants and parameters used in the code.
- truncation(n_r_ic_max(), n_cheb_ic_max(), n_r_ic_maxmag(), n_r_tot(), lm_max(), l_maxmag(), n_r_max(), n_r_totmag(), n_r_maxmag()): This module defines the grid points and the truncation
- precision_mod: This module controls the precision used in MagIC
- fields (work_lmloc()): This module contains the potential fields and their radial derivatives
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- logic (l_rot_ic(), l_mag_nl(), l_lcr(), l_cond_ic(), l_b_nl_cmb(), l_rms(), l_b_nl_icb(), l_update_b()): Module containing the logicals that control the run

Variables

- updateb_mod/jpivot(:,:) [integer,private/allocatable]
- updateb_mod/lbmat(:)[logical,allocatable/public]
- updateb_mod/jmat_fac(:,:) [real,private/allocatable]
- updateb_mod/maxthreads [integer,private]
- updateb_mod/workb (:,:) [complex,private/allocatable]
- updateb_mod/**bpivot** (:,:) [integer,private/allocatable]
- updateb_mod/rhs2 (:,:,:) [complex,private/allocatable]
- updateb_mod/**rhs1** (:,:,:) [complex,private/allocatable]
- updateb_mod/bmat_fac(:,:) [real,private/allocatable]

- updateb_mod/bmat (:,:,:) [real,private/allocatable]
- updateb_mod/jmat(:,:,:) [real,private/allocatable]
- updateb_mod/dtp(:)[complex,private/allocatable]
- updateb_mod/dtt(:)[complex,private/allocatable]

Subroutines and functions

subroutine updateb_mod/**updateb**(b, db, ddb, aj, dj, ddj, dvxbhlm, dbdt, dbdtlast, djdt, djdtlast, b_ic, db_ic, ddb_ic, aj_ic, dj_ic, ddj_ic, dbdt_iclast, djdt_iclast, b_nl_cmb, aj_nl_cmb, aj_nl_icb, omega_ic, w1, coex, dt, time, nlmb, lrmsnext)

Calculated update of magnetic field potential and the time stepping arrays dbdtLast, ...

updates the magnetic field potentials b, aj and their derivatives, adds explicit part to time derivatives of b and j

- **b** (ulmmag-(llmmag)+1,n r maxmag) [complex,inout]
- **db** (*ulmmag-(llmmag)+1,n_r_maxmag*) [*complex,out*]
- **ddb** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,out]
- **aj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,inout]
- **dj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,out]
- **ddj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,out]
- **dvxbhlm** (*ulmmag-(llmmag*)+1,*n_r_maxmag*) [complex,inout]
- **dbdt** (*ulmmag*-(*llmmag*)+1,*n_r_maxmag*) [*complex*,*in*]
- **dbdtlast** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,inout]
- **djdt** (*ulmmag*-(*llmmag*)+1,*n_r_maxmag*) [*complex*,*inout*]
- **djdtlast** (*ulmmag*-(*llmmag*)+1,*n_r_maxmag*) [*complex*,*inout*]
- **b_ic** (*ulmmag-(llmmag)+1,n_r_ic_maxmag*) [*complex,inout*]
- **db_ic** (*ulmmag-(llmmag)+1,n_r_ic_maxmag*) [*complex,out*]
- **ddb_ic** (*ulmmag-(llmmag)+1,n_r_ic_maxmag*) [*complex,out*]
- aj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,inout]
- **dj_ic** (*ulmmag-(llmmag*)+1,*n_r_ic_maxmag*) [*complex,out*]
- **ddj_ic** (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
- **dbdt_iclast** (*ulmmag-(llmmag*)+1,*n_r_ic_maxmag*) [*complex,inout*]
- **djdt_iclast** (*ulmmag-(llmmag)+1,n_r_ic_maxmag*) [complex,inout]

```
b_nl_cmb (*) [complex,in]
aj_nl_cmb (*) [complex,in]
aj_nl_icb (*) [complex,in]
```

• omega_ic [real,in]

• w1 [real,in] :: weight for time step!

• coex [real,in] :: factor depending on alpha

• dt [real,in]

• time [real,in]

• nlmb [integer,in]

• **lrmsnext** [logical,in]

```
Called from lmloop()
```

```
Call to get_bmat(), abortrun(), get_ddr(), get_ddr_even(), hint2pollm(),
    hint2torlm()
```

subroutine updateb_mod/**get_bmat** (*dt*, *l*, *hdif*, *bmat*, *bpivot*, *bmat_fac*, *jmat*, *jpivot*, *jmat_fac*)

Purpose of this subroutine is to contruct the time step matrices bmat(i,j) and ajmat for the dynamo equations.

Parameters

```
• dt [real,in]
```

- I [integer,in]
- hdif [real,in]
- **bmat** (*n_r_totmag*,*n_r_totmag*) [real,out]
- **bpivot** (*n_r_totmag*) [integer,out]
- bmat_fac (n_r_totmag) [real,out]
- **jmat** (*n_r_totmag*,*n_r_totmag*) [real,out]
- **jpivot** (*n_r_totmag*) [integer,out]
- jmat_fac (n_r_totmag) [real,out]

Called from updateb()

Call to abortrun(), prepare_mat()

10.8 Non-linear part of the time stepping (radial loop)

10.8.1 radialLoop.f90

Quick access

Routines finalize_radialloop(), initialize_radialloop(), radialloopg()

Needed modules

- mem_alloc (memwrite(), bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- graphout_mod (graphout_mpi_header()): This module contains the subroutines that store the 3-D graphic files.
- riterthetablocking mod(riterthetablocking t())
- radial_data (n_r_cmb(), n_r_icb(), nrstopmag(), nrstartmag(), nrstop(), nrstart()): This module defines the MPI decomposition in the radial direction.
- precision_mod: This module controls the precision used in MagIC
- parallel_mod (n_procs(), rank()): This module contains the blocking information
- logic (l_rot_ic(), l_mag_nl(), l_dtb(), l_double_curl(), l_chemical_conv(), l_cond_ma(), lverbose(), l_mag_kin(), l_cond_ic(), l_mag_lf(), l_single_matrix(), l_rot_ma(), l_mag()): Module containing the logicals that control the run
- riteration_mod(riteration_t())
- physical_parameters (kbotv(), ktopv()): Module containing the physical parameters
- riterthetablocking_seq_mod(riterthetablocking_seq_t())
- blocking (nthetabs (), sizethetab ()): Module containing blocking information
- constants (zero ()): module containing constants and parameters used in the code.
- truncation(lm_max(), lm_maxmag(), lmp_max(), l_maxmag(), l_max()): This module defines the grid points and the truncation

Variables

Subroutines and functions

```
subroutine radialloop/initialize radialloop()
          Called from magic
          Call to memwrite()
subroutine radialloop/finalize_radialloop()
          Called from magic
subroutine radialloop/radialloopg(l_graph, l_cour, l_frame, time, dt, dtlast, ltocalc, ltonext,
                                           ltonext2, lhelcalc, lpowercalc, lrmscalc, lpresscalc,
                                           lviscbccalc, lfluxprofcalc, lperpparcalc, l_probe_out,
                                           dsdt, dwdt, dzdt, dpdt, dxidt, dbdt, djdt, dvxvhlm,
                                           dvxbhlm, dvsrlm, dvprlm, dvxirlm, lorentz torque ic,
                                           lorentz_torque_ma,
                                                               br\_vt\_lm\_cmb,
                                                                                 br\_vp\_lm\_cmb,
                                           br_vt_lm_icb, br_vp_lm_icb, hellmr, hel2lmr, helnalmr,
                                           helna2lmr, visclmr, uhlmr, duhlmr, gradslmr, fconvlmr,
                                           fkinlmr, fvisclmr, fpoynlmr, freslmr, eperplmr, eparlmr,
```

eperpaxilmr, eparaxilmr, dtrkc, dthkc)

This subroutine performs the actual time-stepping.

- l_graph [logical,in]
- l_cour [logical,in]
- l_frame [logical,in]
- **time** [real,in]
- dt [real,in]
- dtlast [real,in]
- **ltocalc** [logical,in]
- **ltonext** [logical,in]
- ltonext2 [logical,in]
- **lhelcalc** [logical,in]
- **lpowercalc** [logical,in]
- **lrmscalc** [logical,in]
- **lpresscalc** [logical,in]
- lviscbccalc [logical,in]
- **Ifluxprofcalc** [logical,in]
- **lperpparcalc** [logical,in]
- l_probe_out [logical,in]
- **dsdt** (*lm_max,nrstop-(nrstart)*+1) [*complex,out*]
- **dwdt** (*lm_max,nrstop-(nrstart*)+1) [*complex,out*]
- **dzdt** (*lm_max,nrstop-(nrstart)*+1) [*complex,out*]
- **dpdt** (*lm_max,nrstop-(nrstart*)+1) [*complex,out*]
- **dxidt** (*lm_max,nrstop-(nrstart*)+1) [*complex,out*]
- **dbdt** (lm_maxmag,nrstopmag-(nrstartmag)+1) [complex,out]
- **djdt** (lm_maxmag,nrstopmag-(nrstartmag)+1) [complex,out]
- **dvxvhlm** (*lm_max,nrstop-(nrstart*)+1) [*complex,out*]
- **dvxbhlm** (*lm_maxmag,nrstopmag-(nrstartmag)*+1) [*complex,out*]
- **dvsrlm** (*lm_max,nrstop-(nrstart)*+1) [*complex,out*]
- **dvprlm** (*lm_max,nrstop-(nrstart)*+1) [*complex,out*]
- **dvxirlm** (*lm_max,nrstop-(nrstart)*+1) [*complex,out*]
- lorentz_torque_ic [real,out]
- lorentz_torque_ma [real,out]
- **br_vt_lm_cmb** (*lmp_max*) [complex,out] :: product br*vt at CMB
- **br_vp_lm_cmb** (*lmp_max*) [*complex,out*] :: product br*vp at CMB
- **br_vt_lm_icb** (*lmp_max*) [complex,out] :: product br*vt at ICB
- **br_vp_lm_icb** (*lmp_max*) [complex,out] :: product br*vp at ICB

```
• hellmr (l max+1,nrstop-(nrstart)+1) [real,out]
      • hel2lmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • helnalmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • helna2lmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • visclmr (l max+1,nrstop-(nrstart)+1) [real,out]
      • uhlmr (l max+1,nrstop-(nrstart)+1) [real,out]
      • duhlmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • gradslmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • fconvlmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • fkinlmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • fvisclmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • fpoynlmr (l_maxmag+1,nrstopmag-(nrstartmag)+1) [real,out]
      • freslmr (l_maxmag+1,nrstopmag-(nrstartmag)+1) [real,out]
      • eperplmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • eparlmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • eperpaxilmr (l max+1,nrstop-(nrstart)+1) [real,out]
      • eparaxilmr (l_max+1,nrstop-(nrstart)+1) [real,out]
      • dtrkc (nrstop-(nrstart)+1) [real, out]
      • dthkc (nrstop-(nrstart)+1) [real, out]
Called from step_time()
```

10.8.2 rIteration.f90

Quick access

Routines set_steering_variables()

Call to graphout_mpi_header()

Needed modules

• precision_mod: This module controls the precision used in MagIC

Types

```
    type riteration_mod/unknown_type
    Type fields

            % lfluxprofcalc [logical]
            % dthkc [real]
            % lhelcalc [logical]
```

- % lpresscalc [logical]
- % l_probe_out [logical]
- % isradialboundarypoint [logical]
- % nbc[integer]
- % lderiv [logical]
- % nr [integer]
- % 1_frame [logical]
- % 1_graph [logical]
- % lperpparcalc[logical]
- % dtrkc[real]
- % ltonext2 [logical]
- % 1_cour [logical]
- % ltocalc [logical]
- % ltonext [logical]
- % lmagnlbc [logical]
- % lviscbccalc [logical]
- % lrmscalc[logical]
- % lpowercalc[logical]

Subroutines and functions

- this [real]
- l_cour [logical,in]
- **ltocalc** [logical,in]
- **Itonext** [logical,in]
- **ltonext2** [logical,in]
- **Ideriv** [logical,in]
- **lrmscalc** [logical,in]
- **lhelcalc** [logical,in]
- **lpowercalc** [logical,in]
- l_frame [logical,in]
- **lmagnlbc** [logical,in]

- l_graph [logical,in]
- lviscbccalc [logical,in]
- Ifluxprofcalc [logical,in]
- **lperpparcalc** [logical,in]
- **lpresscalc** [logical,in]
- 1 probe out [logical,in]

10.8.3 rIterThetaBlocking.f90

Quick access

```
Routines allocate_common_arrays(), deallocate_common_arrays(), set_thetablocking(), transform_to_grid_space()
```

- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- grid_space_arrays_mod(grid_space_arrays_t())
- nonlinear_lm_mod(nonlinear_lm_t())
- fields (ds_rloc(), xi_rloc(), s_rloc(), p_rloc()): This module contains the potential fields and their radial derivatives
- fft: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- legendre_spec_to_grid (leg_scal_to_spat(), legtfgnomag(), legtfg(), leg_scal_to_grad_spat())
- radial_data(n_r_cmb(), nrstart(), n_r_icb(), nrstop()): This module defines the MPI decomposition in the radial direction.
- precision_mod: This module controls the precision used in MagIC
- legendre_grid_to_spec
- logic (l_rot_ic(), l_chemical_conv(), l_b_nl_icb(), l_mag_nl(), l_dtb(), l_movie_oc(), l_precession(), l_rot_ma(), l_cond_ic(), l_cond_ma(), l_mag_kin(), l_conv_nl(), l_b_nl_cmb(), l_store_frame(), l_heat(), l_mag_lf(), l_anel(), l_tp_form(), l_ht(), l_mag(), l_conv()): Module containing the logicals that control the run
- riteration_mod(riteration_t())
- physical_parameters (n_r_lcr(), kbots(), ktops()): Module containing the physical parameters
- radial_functions (orho1(), or2()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- leg_helper_mod(leg_helper_t())
- blocking (nfs ()): Module containing blocking information
- nonlinear_bcs(v_rigid_boundary())

• truncation(l_max(), n_r_maxstr(), lm_maxmag(), lmp_max_dtb(), lmp_max(), l_axi(), n_theta_maxstr(), lm_max(), nrp(), n_phi_maxstr()): This module defines the grid points and the truncation

Types

```
• type riterthetablocking_mod/unknown_type
```

Type fields

- % bslast (,,*) [real,allocatable]
- % bplast (,,*) [real,allocatable]
- % leg_helper [leg_helper_t]
- % bzlast (,,*) [real,allocatable]
- % nthetabs [integer]
- % sizethetab [integer]

Subroutines and functions

```
subroutine riterthetablocking_mod/allocate_common_arrays(this)
```

Parameters this [real]

subroutine riterthetablocking_mod/deallocate_common_arrays(this)

Parameters this [real]

subroutine riterthetablocking_mod/**set_thetablocking**(this, nthetabs, sizethetab)

Parameters

- this [real]
- **nthetabs** [integer,in]
- **sizethetab** [integer,in]

Parameters

- this [real]
- **nthetastart** [integer,in]
- **nthetastop** [integer,in]
- **gsa** [grid_space_arrays_t]
- time [real,in]

```
Call to legtfg(), legtfgnomag(), leg_scal_to_spat(),
leg_scal_to_grad_spat(), fft_thetab(), v_rigid_boundary()
```

- this [real]
- **nthetastart** [integer,in]
- nthetastop [integer,in]
- **gsa** [grid_space_arrays_t]
- **nl lm** [nonlinear lm t]

Call to fft_thetab(), legtf3(), legtf2(), legtf1(), legtf_spher_tor()

10.8.4 rIterThetaBlocking_OpenMP.f90

Quick access

Routines finalize_riterthetablocking_openmp(), initialize_riterthetablocking_openmp(), do_iteration_thetablocking_openmp()

- probe_mod
- nonlinear_lm_mod(nonlinear_lm_t())
- grid_space_arrays_mod(grid_space_arrays_t())
- graphout_mod(graphout_mpi()): This module contains the subroutines that store the 3-D graphic files.
- constants (zero ()): module containing constants and parameters used in the code.
- nl_special_calc: This module allows to calculcate several diagnostics that need to be computed in the physical space (non-linear quantities)
- truncation (l_max(), n_r_maxstr(), lmp_max_dtb(), lmp_max(), n_theta_maxstr(), lm_max(), nrp(), n_phi_maxstr()): This module defines the grid points and the truncation
- leg_helper_mod(leg_helper_t())
- dtb_arrays_mod(dtb_arrays_t())
- torsional_oscillations (gettonext(), getto(), gettofinish()): This module contains information for TO calculation and output
- to_arrays_mod(to_arrays_t())
- courant_mod(courant())
- blocking (nfs ()): Module containing blocking information
- nonlinear_bcs(get_br_v_bcs())
- radial_functions (orho1(), or2()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- precision_mod: This module controls the precision used in MagIC
- outrot (get_lorentz_torque())
- riterthetablocking_mod(riterthetablocking_t())
- out_movie(store_movie_frame())

- dtb_mod (get_dh_dtblm(), get_dtblm()): This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output....
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- logic (l_to(), l_cond_ma(), l_heat(), l_mag_lf(), l_b_nl_icb(), l_rot_ic(), l_mag(), l_cond_ic(), l_anel(), l_conv_nl(), l_conv(), l_probe(), l_movie_oc(), l_chemical_conv(), l_mag_kin(), l_store_frame(), l_rot_ma(), l_ht(), l_mag_nl(), l_dtb(), l_b_nl_cmb(), l_tp_form()): Module containing the logicals that control the run

Types

• type riterthetablocking_openmp_mod/unknown_type

Type fields

- % **gsa**(*)[grid_space_arrays_t,allocatable]
- % lorentz_torque_ic (*) [real,allocatable]
- % nthreads [integer]
- % dtb_arrays (*) [dtb_arrays_t,allocatable]
- % nl_lm (*) [nonlinear_lm_t,allocatable]
- % to_arrays(*)[to_arrays_t,allocatable]
- % lorentz_torque_ma (*) [real,allocatable]

Subroutines and functions

```
function riterthetablocking_openmp_mod/getthistype(this)
```

Parameters this [real]

Return getthistype [character]

subroutine riterthetablocking_openmp_mod/initialize_riterthetablocking_openmp (this)

Parameters this [real]

subroutine riterthetablocking_openmp_mod/finalize_riterthetablocking_openmp (this)

Parameters this [real]

```
subroutine riterthetablocking_openmp_mod/do_iteration_thetablocking_openmp (this,
                                                                                                      nr,
                                                                                                      nbc,
                                                                                                      time,
                                                                                                      dt,
                                                                                                      dt-
                                                                                                      last.
                                                                                                      dsdt,
                                                                                                      dwdt,
                                                                                                      dzdt,
                                                                                                      dpdt,
                                                                                                      dx-
                                                                                                      idt,
                                                                                                      dbdt,
                                                                                                      djdt,
                                                                                                      dvxvhlm,
                                                                                                      dvxbhlm,
                                                                                                      dvs-
                                                                                                      rlm,
                                                                                                      dvprlm,
                                                                                                      dvxirlm,
                                                                                                      br_vt_lm_cmb,
                                                                                                      br_vp_lm_cmb,
                                                                                                      br\_vt\_lm\_icb,
                                                                                                      br_vp_lm_icb,
                                                                                                      lorentz_torque_ic,
                                                                                                      lorentz_torque_ma,
                                                                                                      hellmr,
                                                                                                      hel2lmr,
                                                                                                      hel-
                                                                                                      nalmr,
                                                                                                      helna2lmr,
                                                                                                      vis-
                                                                                                      clmr,
                                                                                                      uhlmr,
                                                                                                      duhlmr,
                                                                                                      grad-
                                                                                                      slmr,
                                                                                                      fcon-
                                                                                                      vlmr,
                                                                                                      fkinlmr,
                                                                                                      fvis-
                                                                                                      clmr,
                                                                                                      fpoynlmr,
                                                                                                      freslmr,
                                                                                                      eper-
                                                                                                      plmr,
                                                                                                      eparlmr,
                                                                                                      eper-
                                                                                                      рах-
                                                                                                      ilmr,
                                                                                                      eparax-
```

Parameters

ilmr)

- this [real]
- **nr** [integer,in]
- **nbc** [integer,in]
- time [real,in]
- **dt** [real,in]
- dtlast [real,in]
- **dsdt** (*) [complex,out]
- **dwdt** (*) [complex,out]
- **dzdt** (*) [complex,out]
- **dpdt** (*) [complex,out]
- dxidt (*) [complex,out]
- **dbdt** (*) [complex,out]
- **djdt** (*) [complex,out]
- **dvxvhlm** (*) [complex,out]
- dvxbhlm (*) [complex,out]
- **dvsrlm** (*) [complex,out]
- **dvprlm** (*) [complex,out]
- dvxirlm (*) [complex,out]
- br_vt_lm_cmb (*) [complex,out]
- br_vp_lm_cmb (*) [complex,out]
- **br_vt_lm_icb** (*) [complex,out]
- br_vp_lm_icb (*) [complex,out]
- lorentz_torque_ic [real,out]
- lorentz_torque_ma [real,out]
- hellmr (*) [real,out]
- **hel2lmr** (*) [real,out]
- helnalmr (*) [real,out]
- helna2lmr (*) [real,out]
- visclmr (*) [real,out]
- uhlmr (*) [real,out]
- **duhlmr** (*) [real,out]
- gradslmr (*) [real,out]
- fconvlmr (*) [real,out]
- **fkinlmr** (*) [real,out]
- **fvisclmr** (*) [real,out]
- **fpoynlmr** (*) [real,out]

- freslmr (*) [real,out]
- eperplmr (*) [real,out]
- eparlmr (*) [real,out]
- eperpaxilmr (*) [real,out]
- eparaxilmr (*) [real,out]

```
Call to get_br_v_bcs(), get_lorentz_torque(), courant(), graphout_mpi(),
    probe_out(), get_helicity(), get_visc_heat(), get_nlblayers(),
    get_fluxes(), get_perppar(), store_movie_frame(), get_dtblm(),
    gettonext(), getto(), gettofinish(), get_dh_dtblm()
```

10.8.5 get_nl.f90

Types

• type general_arrays_mod/unknown_type

10.8.6 get td.f90

Quick access

```
Routines set_zero(), get_td()
```

- horizontal_data (dtheta3a(), hdif_b(), dphi0(), dtheta4a(), dtheta1a(), dlh(), dtheta2a(), dtheta3s(), hdif_v(), dtheta4s(), dtheta1s(), dphi(), dtheta2s()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- rms (lf2hint(), pre2hint(), clf2hint(), geo2hint(), arcmag2hint(), arc2hint(), cia2hint(), cor2hint(), adv2hint(), mag2hint(), buo2hint(), plf2hint()): This module contains the calculation of thr RMS force balance and induction terms.
- fields (z_rloc(), s_rloc(), ddw_rloc(), dw_rloc(), w_rloc(), p_rloc(), dp_rloc(), dz_rloc()): This module contains the potential fields and their radial derivatives
- rms_helpers (hintrms ()): This module contains several useful subroutines required to compute RMS diagnostics
- precision_mod: This module controls the precision used in MagIC
- logic (l_anelastic_liquid(), l_mag_nl(), l_double_curl(), l_chemical_conv(), l_mag_kin(), l_conv_nl(), l_mag_lf(), l_single_matrix(), l_anel(), l_heat(), l_tp_form(), l_rms(), l_conv(), l_mag(), l_corr()): Module containing the logicals that control the run
- physical_parameters (buofac(), epscxi(), epsc(), vischeatfac(), ra(), n_r_lcr(), thexpnb(), corfac(), ohmlossfac()): Module containing the physical parameters

- truncation (lm_max(), l_max(), lmp_max(), lm_maxmag()): This module defines the grid points and the truncation
- blocking (lmp2lmps(), lm2lms(), lm2lmp(), lm2m(), lm2l(), lmp2lmpa(), st_map(), lm2lma()): Module containing blocking information
- constants (zero(), two()): module containing constants and parameters used in the code.
- radial_functions (alpha0(), orho1(), epscprof(), or4(), rho0(), or2(), or1(), beta(), r(), temp0(), rgrav(), ogrun()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Types

• type nonlinear_lm_mod/unknown_type

Type fields

- % vxirlm(*)[complex,allocatable]
- % vxbrlm(*)[complex,allocatable]
- % vxiplm(*)[complex,allocatable]
- % vstlm(*)[complex,allocatable]
- % ohmlosslm(*)[complex,allocatable]
- % vsplm (*) [complex,allocatable]
- % **vprlm**(*)[complex,allocatable]
- % pfp2lm (*) [complex,allocatable]
- % lfplm (*) [complex,allocatable]
- % lfrlm (*) [complex,allocatable]
- % lftlm(*)[complex,allocatable]
- % advtlm(*)[complex,allocatable]
- % advrlm(*)[complex,allocatable]
- % advplm(*)[complex,allocatable]
- % pft2lm(*)[complex,allocatable]
- % cfp2lm(*)[complex,allocatable]
- % advt21m(*)[complex,allocatable]
- % vsrlm(*)[complex,allocatable]
- % lfp2lm(*)[complex,allocatable]
- % vxbplm(*)[complex,allocatable]
- % vxitlm(*)[complex,allocatable]
- % lft2lm(*)[complex,allocatable]
- % vxbtlm(*)[complex,allocatable]
- % vischeatlm(*)[complex,allocatable]
- % cft2lm(*)[complex,allocatable]

- % advp21m(*)[complex,allocatable]

Subroutines and functions

```
subroutine nonlinear_lm_mod/initialize(this, lmp_max)
```

Parameters

- this [real]
- lmp_max [integer,in]

subroutine nonlinear_lm_mod/finalize(this)

Parameters this [real]

subroutine nonlinear_lm_mod/set_zero(this)

Parameters this [real]

subroutine nonlinear_lm_mod/output (this)

Parameters this [real]

subroutine nonlinear_lm_mod/**get_td**(*this*, *nr*, *nbc*, *lrmscalc*, *lpresscalc*, *dvsrlm*, *dvxvrlm*, *dvxvhlm*, *dvxvhlm*, *dvxbhlm*, *dwdt*, *dzdt*, *dpdt*, *dsdt*, *dbdt*, *djdt*)

Purpose of this to calculate time derivatives dwdt,dzdt,dpdt,dsdt,dxidt,dbdt,djdt and auxiliary arrays dVSrLM, dVXirLM and dVxBhLM, dVxVhLM from non-linear terms in spectral form, contained in flmw1-3,flms1-3, flmb1-3 (input)

Parameters

- this [real]
- **nr** [integer,in]
- **nbc** [integer,in] :: signifies boundary conditions
- **Irmscalc** [logical,in]
- **lpresscalc** [logical,in]
- **dvsrlm** (*) [complex,out]
- **dvprlm** (*) [complex,out]
- **dvxirlm** (*) [complex,out]
- **dvxvhlm** (*) [complex,out]
- **dvxbhlm** (*) [complex,out]
- **dwdt** (*) [complex,out]
- **dzdt** (*) [complex,out]
- **dpdt** (*) [complex,out]
- **dsdt** (*) [complex,out]
- dxidt (*) [complex,out]
- **dbdt** (*) [complex,out]
- **djdt** (*) [complex,out]

Call to hintrms ()

10.8.7 nonlinear bcs.f90

Quick access

Routines get_b_nl_bcs(), get_br_v_bcs(), v_rigid_boundary()

Needed modules

- horizontal_data (phi(), dthetala(), dlh(), sn2(), o_sin_theta(), dthetals(), dphi(), sintheta(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- legendre_grid_to_spec(legtf2())
- useful (abortrun ()): library with several useful subroutines
- fft (fft_thetab()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- precision_mod: This module controls the precision used in MagIC
- logic (l_diff_prec()): Module containing the logicals that control the run
- physical_parameters (po_diff(), diff_prec_angle(), prmag(), sigma_ratio(), oek(), conductance ma()): Module containing the physical parameters
- truncation (1_axi(), nrp(), n_phi_max(), 1mp_max()): This module defines the grid points and the truncation
- blocking (lmp2lmps(), lm2lmp(), sizethetab(), lm2m(), lm2l(), nfs(), lmp2lmpa()): Module containing blocking information
- constants (two ()): module containing constants and parameters used in the code.
- radial_functions (r_cmb(), r_icb(), rho0()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

Subroutines and functions

Purpose of this subroutine is to calculate the nonlinear term of the magnetic boundary condition for a conducting mantle or inner core in space (r,lm). Calculation is performed for the theta block:

```
\label{lem:n_theta_min} $$ n\_theta\_min+n\_theta\_block-1 $$
```

On input br, vt and vp are given on all phi points and thetas in the specific block. On output the contribution of these grid points to all degree and orders is stored in br_vt_lm and br_vp_lm. Output is [r/sin(theta)*Br*U]=[(0,br_vt_lm,br_vp_lm)]

```
• br (nrp,*) [real,in] :: r**2 * B r
                • vt (nrp,*) [real,in] :: r*sin(theta) U_theta
                • vp (nrp,*) [real,in] :: r*sin(theta) U_phi
                • omega [real,in] :: rotation rate of mantle or IC
                • o r e 2 [real,in] :: 1/r**2
                • o rho [real,in] :: 1/rho0 (anelastic)
                • n_theta_min [integer,in] :: start of theta block
                • n_theta_block [integer,in] :: size of theta_block
                • br_vt_lm (lmp_max) [complex,inout]
                • br_vp_lm (lmp_max) [complex,inout]
          Called from do_iteration_thetablocking_openmp(), do_iteration_thetablocking_seq(),
              do_iteration_thetablocking_shtns()
          Call to fft thetab(), legtf2()
subroutine nonlinear_bcs/get_b_nl_bcs(bc, br_vt_lm, br_vp_lm, lm_min_b, lm_max_b,
                                                  b nl bc, aj nl bc)
```

Parameters

- **bc** [character,in] :: Distinguishes 'CMB' and 'ICB'
- **br** vt lm (lmp max) [complex, in] :: [br*vt/(r**2*sin(theta)**2)]
- **br_vp_lm** (*lmp_max*) [*complex,in*] :: [br*vp/(r**2*sin(theta)**2)
- **Im min b** [integer,in] :: limits of lm-block
- lm_max_b [integer,in] :: nonlinear bc for aj
- **b_nl_bc** (lm_max_b-lm_min_b+1) [complex,out]
- aj_nl_bc (lm_max_b-lm_min_b+1) [complex,out]

Called from step_time()

Call to abortrun()

subroutine nonlinear_bcs/**v_rigid_boundary** (nr, omega, lderiv, vrr, vtr, vpr, cvrr, dvrdtr, *dvrdpr*, *dvtdpr*, *dvpdpr*, *nthetastart*, *time*)

> Purpose of this subroutine is to set the velocities and their derivatives at a fixed boundary. While vt is zero, since we only allow for rotation about the z-axix, vp= r sin(theta) v_phi = r**2 sin(theta)**2 omega cvr= $r^{**}2$ * radial component of (curl v) = $r^{**}2$ 2 cos(theta) omega

- **nr** [integer,in] :: no of radial grid point
- omega [real,in]
- **Ideriv** [logical,in] :: derivatives required?
- **vrr** (*nrp*,*nfs*) [real,out]
- vtr (nrp,nfs) [real,out]
- **vpr** (*nrp*,*nfs*) [real,out]

```
• cvrr (nrp,nfs) [real,out]
```

- **dvrdtr** (*nrp*,*nfs*) [real,out]
- **dvrdpr** (nrp,nfs) [real,out]
- **dvtdpr** (*nrp*,*nfs*) [real,out]
- **dvpdpr** (*nrp*,*nfs*) [real,out]
- **nthetastart** [integer,in] :: no of theta to start with
- time [real,in]

Called from transform_to_grid_space(), transform_to_grid_space_shtns()

10.9 Chebyshev polynomials and cosine transforms

10.9.1 chebyshev_polynoms.f90

Quick access

```
Routines cheb_grid(), get_chebs_even()
```

Needed modules

- precision_mod: This module controls the precision used in MagIC
- num_param (map_function()): Module containing numerical and control parameters
- constants (one (), four (), pi (), two (), half ()): module containing constants and parameters used in the code.
- logic (l_newmap ()): Module containing the logicals that control the run

Variables

Subroutines and functions

Construct even Chebychev polynomials and their first, second and third derivative up to degree $2*(n_r/2)$ at $(n_r/2)$ points x in the interval [a,b]. Since the Chebs are only defined in [-1,1] we have to map the points x in [a,b] onto points y in the interval [-1,1]. This map is contructed by the subroutine cheb_x_map_e.f which must be called before entering this subroutine. For even Chebs we need only half the point of the map, these $(n_r/2)$ points are in the interval [1,0]. NOTE the reversed order in the points: y(1)=-1, $y(n_r)=1$. y=0 is not used, which helps to avoid singularities.

- **n_r** [integer,in] :: number of grid points
- a [real,in] :: interval boundaries [a,b]
- **b** [real,in]

- y (n_r_max) [real,in] :: n_r grid points in interval [a,b]
- **n_r_max** [integer,in,] :: max number of radial points, dims of y
- **cheb** (dim1,dim2) [real,out] :: cheb(i,j) is Chebychev pol.
- dcheb (dim1,dim2) [real,out] :: first derivative of cheb
- **d2cheb** (dim1,dim2) [real,out] :: second derivative o cheb
- **dim1** [integer,in] :: dimensions of cheb,dcheb,.....
- dim2 [integer,in]

Called from radial()

subroutine chebyshev_polynoms_mod/**cheb_grid**(a, b, n, x, y, a1, a2, x0, lbd, l_map)

Given the interval [a,b] the routine returns the n+1 points that should be used to support a Chebychev expansion. These are the n+1 extrema y(i) of the Chebychev polynomial of degree n in the interval [-1,1]. The respective points mapped into the interval of question [a,b] are the x(i).

Note: x(i) and y(i) are stored in the reversed order: x(1)=b, x(n+1)=a, y(1)=1, y(n+1)=-1

Parameters

- a [real,in] :: interval boundaries
- **b** [real,in]
- n [integer,in] :: degree of Cheb polynomial to be represented by the grid points
- \mathbf{x} (*) [real,out] :: grid points in interval [a,b]
- **y** (*) [real, out] :: grid points in interval [-1,1]
- **a1** [real,in]
- **a2** [real,in]
- **x0** [real,in]
- **lbd** [real,in]
- **l_map** [logical,in] :: Chebyshev mapping

Called from initialize_mapping(), chebintinit(), radial()

10.9.2 cosine_transform_odd.f90

- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (abortrun (), factorise ()): library with several useful subroutines
- precision_mod: This module controls the precision used in MagIC
- fft_fac_mod(fft_fac_complex(), fft_fac_real())
- constants (cos36(), sin36(), cos72(), two(), one(), sin72(), sin60(), half(), pi()): module containing constants and parameters used in the code.

• truncation (lm_max(), lm_max_real()): This module defines the grid points and the truncation

Types

Subroutines and functions

```
subroutine cosine_transform_odd/initialize(this, n, ni, nd)
```

Purpose of this subroutine is to calculate and store several values that will be needed for a fast cosine transform of the first kind. The actual transform is performed by the subroutine costf1.

Parameters

- this [real]
- **n** [integer,in]
- **ni** [integer,in]
- **nd** [integer,in]

Call to abortrun(), factorise()

```
subroutine cosine_transform_odd/finalize(this)
```

```
Parameters this [real]
```

```
subroutine cosine_transform_odd/costf1_complex(this, f, n_f_max, n_f_start, n_f_stop, f2)
```

Purpose of this subroutine is to perform a multiple cosine transforms for n+1 datapoints on the columns numbered n_f_start to n_f_stop in the array f(n_f_max,n+1) Depending whether the input f contains data or coeff arrays coeffs or data are returned in f.

Parameters

- this [real]
- **f** (n f max,*) [complex,inout]
- n_f_max [integer,in,]
- n_f_start [integer,in]
- n_f_stop [integer,in]
- **f2** (n_f_max,*) [complex,out]

Call to fft_fac_complex()

subroutine cosine_transform_odd/costf1_complex_1d(this, f, f2)

Parameters

• this [real]

```
• f(*) [complex,inout]
• f2 (*) [complex,out]

Call to fft_fac_complex()

subroutine cosine_transform_odd/costf1_real(this, f, n_f_max, n_f_start, n_f_stop, f2)

Parameters
• this [real]
• f(n_f_max,*) [real,inout]
• n_f_max [integer,in,]
• n_f_start [integer,in]
```

• **n_f_stop** [integer,in]

• **f2** (n_f_max,*) [real,out]

Call to fft_fac_real()

subroutine cosine_transform_odd/**costf1_real_1d**(*this*, *f*, *f*2)

Parameters

- this [real]
- **f** (*) [real,inout]
- **f2** (*) [real,out]

Call to fft_fac_real()

10.9.3 cosine_transform_even.f90

Quick access

Routines costf2()

Needed modules

- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (abortrun(), factorise()): library with several useful subroutines
- precision_mod: This module controls the precision used in MagIC
- fft_fac_mod(fft_fac_complex())
- constants (cos36(), sin36(), cos72(), two(), one(), sin72(), sin60(), half(), pi()): module containing constants and parameters used in the code.
- truncation (lm_max()): This module defines the grid points and the truncation

Types

```
• type cosine_transform_even/unknown_type
```

Type fields

- % i_costf_init (*) [integer,allocatable]
- % d_costf_init (*) [real,allocatable]

Subroutines and functions

```
subroutine cosine_transform_even/initialize(this, n, ni, nd)
```

Purpose of this subroutine is to calculate several things needed for the cheb transform. Prepares costf2 for even number of grid points.

Parameters

- this [real]
- **n** [integer,in]
- ni [integer,in]
- **nd** [integer,in]

Call to abortrun(), factorise()

```
subroutine cosine transform even/finalize(this)
```

Parameters this [real]

```
subroutine cosine_transform_even/costf2 (this, f, n_f_max, n_f_start, n_f_stop, f2, isign)
```

Purpose of this subroutine is to perform a multiple cosine transforms for n+1 datapoints on the columns numbered n_f _start to n_f _stop in the array $y(n_f_max,n+1)$ Depending whether the input y contains data or coeff arrays coeffs or data are returned in y.

Parameters

- this [real]
- **f** (n_f_max,*) [complex,inout] :: data/coeff input
- **n_f_max** [integer,in,] :: number of columns in y,y2
- n_f_start [integer,in] :: columns to be transformed
- **n f stop** [integer,in]
- **f2** (n_f_max,*) [complex,out] :: work array of the same size as y
- **isign** [integer,in] :: = +1 (-1) for forward (backward) transform

Call to fft_fac_complex()

10.9.4 fft fac.f90

Quick access

```
Routines fft_fac_real(), fft_fac_complex()
```

Needed modules

- precision_mod: This module controls the precision used in MagIC
- constants (cos36(), sin36(), cos72(), sin72(), sin60(), half()): module containing constants and parameters used in the code.

Variables

Subroutines and functions

```
subroutine fft_fac_mod/fft_fac_real (a, b, c, d, trigs, nv, l1, l2, n, ifac, la) main part of Fourier / Chebychev transform called in costf1, costf2
```

Parameters

- **a** (*) [real,in]
- **b** (*) [real,in]
- **c** (*) [real,out]
- **d** (*) [real,out]
- **trigs** (2 * n) [real,in]
- **nv** [integer,in]
- **l1** [integer,in]
- 12 [integer,in]
- **n** [integer,in,]
- ifac [integer,in]
- la [integer,in]

```
subroutine fft_fac_mod/fft_fac_complex (a, b, c, d, trigs, nv, l1, l2, n, ifac, la) main part of Fourier / Chebychev transform called in costf1, costf2
```

- **a** (*) [complex,in]
- **b** (*) [complex,in]
- **c** (*) [complex,out]
- **d** (*) [complex,out]
- **trigs** (2 * n) [real,in]

- **nv** [integer,in]
- **l1** [integer,in]
- **12** [integer,in]
- **n** [integer,in,]
- **ifac** [integer,in]
- la [integer,in]

Called from costf2()

10.10 Legendre transforms

```
10.10.1 plms.f90
```

Quick access

```
Routines plm_theta()
```

Needed modules

- precision_mod: This module controls the precision used in MagIC
- useful (abortrun()): library with several useful subroutines
- constants (osq4pi(), two(), one()): module containing constants and parameters used in the code.

Variables

Subroutines and functions

Parameters

- theta [real,in] :: angle in degrees
- max_degree [integer,in] :: required max degree of plm
- max_order [integer,in] :: required max order of plm
- m0 [integer,in] :: basic wave number
- plma (ndim_plma) [real,out] :: ass. legendres at theta
- **dtheta_plma** (ndim_plma) [real,out] :: their theta derivative
- ndim_plma [integer,in] :: dimension of plma and dtheta_plma
- **norm** [integer,in] :: =0 fully normalised

```
Called from outto(), lnpas2tr(), horizontal(), outpv(), getegeos(),
  initialize_magnetic_energy()
```

Call to abortrun()

10.10.2 legendre_helpers.f90

Quick access

Routines finalize(), initialize(), legprepg(), legprep(), legprep_ic()

Needed modules

- horizontal_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- fields (aj_rloc(), ddw_rloc(), dj_rloc(), b_rloc(), ddb_rloc(), db_rloc(), dw_rloc(), w_rloc(), z_rloc(), omega_ic(), dz_rloc(), omega_ma()): This module contains the potential fields and their radial derivatives
- torsional_oscillations (ddzasl()): This module contains information for TO calculation and output
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- precision_mod: This module controls the precision used in MagIC
- constants (zero(), two(), one()): module containing constants and parameters used in the code.
- logic(l_movie_oc(), l_mag_lf(), l_mag(), l_mag_kin(), l_conv()): Module containing the logicals that control the run
- truncation (lm_max(), l_max(), l_axi(), n_m_max()): This module defines the grid points and the truncation
- blocking (lm2m(), lm2l(), lm2()): Module containing blocking information
- special (lgrenoble(), ddb0(), b0(), db0()): This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- radial_functions (or2()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Types

type leg_helper_mod/unknown_type

Type fields

- % bcmb (*) [complex, allocatable]
- % omegaic [real]
- % dlhz (*) [complex, allocatable]
- % bhc (*) [complex,allocatable]
- % **dlhw** (*) [complex, allocatable]
- % bhg (*) [complex,allocatable]
- % omegama [real]

- % dlhj (*) [complex,allocatable]
- % **zas** (*) [real, allocatable]
- % dzas (*) [real,allocatable]
- % ddzas (*) [real,allocatable]
- % **dlhdw** (*) [complex, allocatable]
- % dvhdrg (*) [complex,allocatable]
- % dlhb (*) [complex,allocatable]
- % cbhg (*) [complex,allocatable]
- % vhg(*)[complex,allocatable]
- % cbhc (*) [complex,allocatable]
- % **vhc** (*) [complex,allocatable]
- % dvhdrc (*) [complex,allocatable]

Variables

Subroutines and functions

subroutine leg_helper_mod/initialize(this, lm_max, lm_maxmag, l_max)

Parameters

- this [real]
- lm_max [integer,in]
- lm_maxmag [integer,in]
- l_max [integer,in]

subroutine leg_helper_mod/finalize(this)

Parameters this [real]

Purpose of this subroutine is to prepare Legendre transforms from (r,l,m) space to (r,theta,m) space by calculating auxiliary arrays dpdw,dpddw, dLhj which contain combinations of harmonic coeffs multiplied with (l,m)-dependend factors as well as the radial dependence:

- nBc =0 standard inner radial grid point
- nBc =1 radial velocity zero, spatial derivs not needed
- nBc =2 all velocity comp. zero, spatial derivs not needed

lDeriv=.true. field derivatives required

- this [real]
- **nr** [integer,in] :: radial level
- **nbc** [integer,in] :: boundary condition

- **Ideriv** [logical,in] :: get also field derivatives!
- **Irmscalc** [logical,in] :: Rms force balance ?
- **l_frame** [logical,in] :: Calculate movie frame?
- **Itonext** [logical,in] :: for TO output
- **ltonext2** [logical,in]
- **ltocalc** [logical,in]

subroutine leg_helper_mod/**legprep** (w, dw, ddw, z, dz, dlh, lm_max, l_max, minc, r, lderiv, lhor, dlhw, vhg, vhc, dlhz, cvhg, cvhc)

Purpose of this subroutine is to prepare Legendre transforms from (r,l,m) space to (r,theta,m) space by calculating auxiliary arrays w, dw, ddw, which contain combinations of harmonic coeffs multiplied with (l,m)-dependend factors as well as possible the radial dependencies.

1Deriv=.true. field derivatives required for curl of field

Parameters

- w (lm_max) [complex,in]
- **dw** (*lm_max*) [*complex*,*in*]
- **ddw** (*lm_max*) [complex,in]
- **z** (lm_max) [complex,in]
- **dz** (*lm_max*) [*complex*,*in*]
- **dlh** (*lm_max*) [real,in]
- lm_max [integer,in,]
- l_max [integer,in]
- minc [integer,in]
- **r** [real,in]
- Ideriv [logical,in]
- **lhor** [logical,in]
- **dlhw** (*lm_max*) [complex,out]
- **vhg** (*lm_max*) [*complex,out*]
- **vhc** (*lm_max*) [*complex,out*]
- **dlhz** (*lm_max*) [*complex,out*]
- **cvhg** (*lm_max*) [*complex,out*]
- **cvhc** (*lm_max*) [*complex,out*]

Called from fields_average()

subroutine leg_helper_mod/**legprep_ic**(w, dw, ddw, z, dz, dlh, lm_max, l_max, minc, r, r_icb, lderiv, lhor, lcondic, dlhw, vhg, vhc, dlhz, cvhg, cvhc)

Purpose of this subroutine is to prepare Legendre transforms from (r,l,m) space to (r,theta,m) space by calculating auxiliary arrays dLhw,vhG,...... which contain combinations of harmonic coeffs multiplied with (l,m)-dependend factors as well as possible the radial dependencies.

1Deriv=.true. field derivatives required for curl of field

Note: This routine is used for the inner core magnetic field which has a special radial function ansatz. It can also be used to prepare the calculation of a field in an insulating inner core for lCondIC=.false.. For this the w has to be the outer core poloidal field and nR is the grid point for the ICB. In any case legTF can be used for the following Legendre transform and fftJW for the Fourier transform.

Parameters

```
• w (lm_max) [complex,in]
```

- **dw** (*lm_max*) [*complex*,*in*]
- **ddw** (*lm_max*) [complex,in]
- **z** (lm_max) [complex,in]
- dz (lm_max) [complex,in]
- **dlh** (*lm_max*) [real,in]
- lm_max [integer,in,]
- l_max [integer,in]
- minc [integer,in]
- **r** [real,in]
- **r_icb** [real,in]
- Ideriv [logical,in]
- **lhor** [logical,in]
- lcondic [logical,in]
- **dlhw** (*lm_max*) [complex,out]
- **vhg** (*lm_max*) [*complex,out*]
- **vhc** (*lm_max*) [*complex,out*]
- **dlhz** (*lm_max*) [complex,out]
- **cvhg** (*lm_max*) [*complex,out*]
- cvhc (lm_max) [complex,out]

Called from graphout_ic(), store_movie_frame_ic()

10.10.3 legendre_spec_to_grid.f90

Quick access

```
Routines lmas2pt(), legtf(), legtfg(), legtfgnomag(),
leg_scal_to_grad_spat(), leg_scal_to_spat()
```

Needed modules

• horizontal_data(dplm(), d_mc2m(), lstop(), lmodd(), osn2(), plm(), lstart()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order

- parallel_mod (rank ()): This module contains the blocking information
- useful (abortrun ()): library with several useful subroutines
- precision_mod: This module controls the precision used in MagIC
- leg_helper_mod(leg_helper_t())
- blocking (lm2mc(), lm2(), nfs(), sizethetab()): Module containing blocking information
- constants (zero(), one(), half()): module containing constants and parameters used in the code.
- truncation (lm_max(), l_max(), nrp(), l_axi(), n_m_max()): This module defines the grid points and the truncation

Variables

Subroutines and functions

Legendre transform from (nR,l,m) to (nR,nTheta,m) [spectral to grid] where nTheta numbers the colatitudes and l is the degree of the spherical harmonic representation.

Transforms entropy, velocity and magnetic field components and terms involving spatial derivatives. The symmetry properties of the P_lm with respect to the equator are used. The equatorially antisymmetric (EA) contribution is added to (subracted from) the equatorially symmetric (ES) contribution in northern (southern) hemisphere.

- nBc: (input) accounts for special conditions on radial boundaries
 - -nBc=2 [we are dealing with a no slip boundary, v_r and v_theta are] zero and v_phi=r sin(theta) omega, where omega is the rotation rate of the boundary (mantle of IC), only magn. field terms are calculated, v is set later.
 - -nBc=1 [a free slip bounday: v_r is zero, derivatives of v and B] are not needed, only components of v,B and entropy are calculated
 - -nBc=0: normal case, interior grid point
- IDeriv=.true. : (input) calculate derivatives
- nThetaStart: (input) transformation is done for the range of points nThetaStart <= nTheta <= nThetaStart-1+sizeThetaB
- Plm: associated Legendre polynomials
- dPlm: sin(theta) d Plm / d theta
- osn2 : 1/sin(theta)^2
- vrc,, : (output) components in (nTheta,m)-space
- dLhw,...,cbhC: (input) help arrays calculated in s_legPrep.f

- **nbc** [integer,in]
- **Ideriv** [logical,in]
- **nthetastart** [integer,in]

- **vrc** (*nrp*,*nfs*) [real,out]
- **vtc** (*nrp*,*nfs*) [real,out]
- **vpc** (*nrp*,*nfs*) [real,out]
- **dvrdrc** (*nrp*,*nfs*) [real,out]
- **dvtdrc** (*nrp*,*nfs*) [real,out]
- **dvpdrc** (*nrp*,*nfs*) [real,out]
- cvrc (nrp,nfs) [real,out]
- **dvrdtc** (*nrp*,*nfs*) [real,out]
- **dvrdpc** (*nrp*,*nfs*) [real,out]
- **dvtdpc** (*nrp*,*nfs*) [real,out]
- **dvpdpc** (nrp,nfs) [real,out]
- **brc** (*nrp*,*nfs*) [real,out]
- **btc** (*nrp*,*nfs*) [real,out]
- **bpc** (*nrp*,*nfs*) [real,out]
- **cbrc** (*nrp*,*nfs*) [real,out]
- **cbtc** (nrp,nfs) [real,out]
- **cbpc** (*nrp*,*nfs*) [real,out]
- leg_helper [leg_helper_t]

Called from transform_to_grid_space()

Same as legTFG for non-magnetic cases

- **nbc** [integer,in]
- Ideriv [logical,in]
- **nthetastart** [integer,in]
- **vrc** (*nrp*,*nfs*) [real,out]
- **vtc** (*nrp*,*nfs*) [real,out]
- **vpc** (*nrp*,*nfs*) [real,out]
- **dvrdrc** (*nrp*,*nfs*) [real,out]
- **dvtdrc** (*nrp*,*nfs*) [real,out]
- **dvpdrc** (nrp,nfs) [real,out]
- **cvrc** (*nrp*,*nfs*) [real,out]
- **dvrdtc** (*nrp*,*nfs*) [real,out]
- **dvrdpc** (nrp,nfs) [real,out]

- **dvtdpc** (nrp,nfs) [real,out]
- **dvpdpc** (nrp,nfs) [real,out]
- **leg_helper** [leg_helper_t]

Called from transform_to_grid_space()

'Legendre transform' from (nR,l,m) to (nR,nTheta,m) [spectral to grid] where nTheta numbers the colatitudes and l and m are degree and order of the spherical harmonic representation.

Calculates all three spherical components vrc,vtc,vpc of a field as well as its curl (cvrc,cvtc,cvpc) that is given a spherical harmonis poloidal toroidal decomposition. s_legPrep.f has to be called first and provides the input fields dLhW, The symmetry properties of the P_lm with respect to the equator are used. The equatorially anti-symmetric (EA) contribution is added to (subracted from) the equatorially symmetric (ES) contribution in northern (southern) hemisphere.

Output is given for all sizeThetaB colatitudes in a colatitude block that starts with colatitude nThetaStart. At output, each component in the northern hemisphere is followed by the component in the southern hemisphere. The Plms and dPlms=sin(theta) d Plm / d theta are only given for the colatitudes in the northern hemisphere.

- dLhw,...,cvhC: (input) arrays provided by legendre helpers.f90
- 1_max: (input) maximum spherical harmonic degree
- minc: (input) azimuthal symmetry
- nThetaStart: (input) transformation is done for the range of points nThetaStart <= nTheta <= nThetaStart-1+sizeThetaB
- sizeThetaB : (input) size theta block
- Plm: (input) associated Legendre polynomials
- dPlm: (input) sin(theta) d Plm / d theta
- lHor=.true. : (input) calculate horizontal componenst
- lDeriv=.true. : (input) calculate curl of field
- vrc, ...,cvpc : (output) components in (nTheta,m)-space

- dlhw (*) [complex,in]
- **vhg** (*) [complex,in]
- **vhc** (*) [complex,in]
- **dlhz** (*) [complex,in]
- cvhg (*) [complex,in]
- **cvhc** (*) [complex,in]
- l_max [integer,in]
- minc [integer,in]
- nthetastart [integer,in]

```
• sizethetab [integer,in]
                • plm (lm_max,*) [real,in]
                • dplm (lm_max,*) [real,in]
                • lhor [logical,in]
                • Ideriv [logical,in]
                • vrc (nrp,*) [real,out]
                • vtc (nrp,*) [real,out]
                • vpc (nrp,*) [real,out]
                • cvrc (nrp,*) [real,out]
                • cvtc (nrp,*) [real,out]
                • cvpc (nrp,*) [real,out]
          Called from fields_average(), graphout_ic(), store_movie_frame_ic()
          Call to abortrun()
subroutine legendre_spec_to_grid/leg_scal_to_spat (nthetastart, slm, sc)
          Legendre transform from (l) to (theta) for a scalar input field
          Parameters
                • nthetastart [integer,in]
                • slm (lm_max) [complex,in]
                • sc (nrp,nfs) [real,out]
          Called from transform_to_grid_space()
subroutine legendre_spec_to_grid/leg_scal_to_grad_spat (nthetastart,
                                                                                       slm,
                                                                                             gradtc,
                                                                          gradpc)
          Transform s(l) into dsdt(theta) and dsdp(theta)
          Parameters
                • nthetastart [integer,in]
                • slm (lm_max) [complex,in]
                • gradtc (nrp,nfs) [real,out]
```

• gradpc (nrp,nfs) [real,out]

Called from transform_to_grid_space()

subroutine legendre_spec_to_grid/lmas2pt (alm, aij, nthetastart, nthetablocksize)

Spherical harmonic transform from alm(l) to aij(theta) Done within the range [nThetaStart,n_thetaStart+nThetaBlockSize-1] only considering axisymmetric contributions. alm contains only m=0 coefficients

Parameters

• **alm** (*) [real,in] :: field in (1,m)-space

- aij (*) [real,out] :: field in (theta,phi)-space
- **nthetastart** [integer,in] :: first theta to be treated
- nthetablocksize [integer,in]

Called from get_power(), outpar(), outhelicity(), outperppar()

10.10.4 legendre_grid_to_spec.f90

Quick access

```
Routines legtfas2(), legtfas(), legtf1(), legtf2(), legtf_spher_tor(), legtf3()
```

Needed modules

- precision_mod: This module controls the precision used in MagIC
- horizontal_data (d_mc2m(), wplm(), lmoddp(), wdplm(), lstopp(), lstartp()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- blocking (nfs(), sizethetab()): Module containing blocking information
- constants (ci ()): module containing constants and parameters used in the code.
- truncation(n_theta_max(), nrp(), n_m_max(), lmp_max()): This module defines the grid points and the truncation

Variables

Subroutines and functions

```
subroutine legendre_grid_to_spec/legtf1 (nthetastart, fllm, fltm)
```

Legendre transform (n_r,n_theta,m) to (n_r,l,m) [grid to spectral] for 2 arrays f1TM (input) to f1LM (output) One call to this routine does part of the transform by summation over theta points in one theta block: nThetaStart,..,nThetaStart+n_theta_block-1

Parameters

- **nthetastart** [integer,in] :: First no of theta on block
- **f1lm** (*lmp_max*) [*complex*, *inout*]
- **f1tm** (*nrp*,*nfs*) [real,in]

Called from initv(), inits(), initxi(), transform_to_lm_space()

```
subroutine legendre_grid_to_spec/legtf2 (nthetastart, fllm, f2lm, f2tm)
```

Legendre transform (n_r,n_theta,m) to (n_r,l,m) [grid to spectral] for 2 arrays f1TM,f2TM (input) to f1LM,f2LM (output) One call to this routine does part of the transform by summation over theta points in on theta block: nThetaStart,...,nThetaStart+n theta block-1

- **nthetastart** [integer,in] :: First no of theta on block
- **f1lm** (*lmp_max*) [*complex*, *inout*]
- **f2lm** (*lmp_max*) [*complex,inout*]
- **f1tm** (*nrp*,*nfs*) [real,in]
- **f2tm** (*nrp*,*nfs*) [*real*,*in*]

Called from get_br_v_bcs(), transform_to_lm_space(), get_dtblm()

subroutine legendre_grid_to_spec/legtf3 (nthetastart, fllm, f2lm, f3lm, f1tm, f2tm, f3tm)

Legendre transform (n_r,n_theta,m) to (n_r,l,m) [grid to spectral] for 2 arrays ancl1/2/3 (input) to flm1/2/3 (output) One call to this routine does part of the transform by summation over theta points in on theta block: nThetaStart,...,nThetaStart+n_theta_block-1

Parameters

- **nthetastart** [integer,in] :: First no of theta on block
- **f1lm** (*lmp_max*) [*complex*, *inout*]
- **f2lm** (*lmp_max*) [*complex*, *inout*]
- **f3lm** (*lmp_max*) [*complex,inout*]
- **f1tm** (*nrp*,*nfs*) [real,in]
- **f2tm** (*nrp*,*nfs*) [real,in]
- **f3tm** (*nrp*,*nfs*) [*real*,*in*]

Called from transform_to_lm_space(), get_dtblm()

subroutine legendre_grid_to_spec/legtf_spher_tor(nthetastart, f1lm, f2lm, f1tm, f2tm)

Vector Legendre transform $vt(n_r,n_t)$, $vp(n_r,n_t)$ to Spheroidal (n_r,l,m) and Toroidal (n_r,l,m)

Parameters

- **nthetastart** [integer,in] :: First no of theta on block
- **f1lm** (*lmp max*) [complex,inout]
- **f2lm** (*lmp_max*) [*complex*, *inout*]
- **f1tm** (*nrp*,*nfs*) [real,in]
- **f2tm** (*nrp*,*nfs*) [*real*,*in*]

Called from transform_to_lm_space()

subroutine legendre_grid_to_spec/legtfas(flm1, ft1, lmmax, nthetastart, sizethetab)

Legendre transform (n_r,n_theta,m) to (n_r,l,m) [grid to spectral] for 2 arrays ancl1/2 (input) to flm1/2 (output) One call to this routine does part of the transform by summation over theta points in on theta block: n_theta_min,..,n_theta_min+n_theta_block-1

- flm1 (*) [real,out]
- **ft1** (*) [real,in]

- **Immax** [integer,in] :: Number of modes to be processed
- **nthetastart** [integer,in] :: First no of theta on block
- sizethetab [integer,in] :: Size of theta block

```
Called from outto(), get_visc_heat(), get_nlblayers(), get_fluxes()
```

```
subroutine legendre_grid_to_spec/legtfas2 (flm1, flm2, ft1, ft2, lmmax, nthetastart, size-thetab)
```

Legendre transform (n_r,n_theta,m) to (n_r,l,m) [grid to spectral] for 2 arrays ancl1/2 (input) to flm1/2 (output) One call to this routine does part of the transform by summation over theta points in on theta block: n_theta_min,..,n_theta_min+n_theta_block-1

Parameters

- flm1 (*) [real,out]
- flm2 (*) [real,out]
- **ft1** (*) [real,in]
- ft2 (*) [real,in]
- Immax [integer,in] :: Number of modes to be processed
- **nthetastart** [integer,in] :: First no of theta on block
- **sizethetab** [integer,in] :: Size of theta block

```
Called from get_perppar(), outto(), get_nlblayers(), get_fluxes(),
    get_helicity(), getto()
```

10.11 Fourier transforms

10.11.1 fft.f90

Description

This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5

Quick access

```
Variables nd, ni, i_fft_init, d_fft_init
Routines finalize_fft(), wpass3jw(), wpass4jw(), wpass5jw(), wpass2jw(),
    fftjw(), fft99ajw(), fft_thetab(), fft_to_real(), init_fft(), fft99bjw()
```

Needed modules

- parallel_mod: This module contains the blocking information
- useful (abortrun (), factorise ()): library with several useful subroutines
- precision_mod: This module controls the precision used in MagIC
- blocking: Module containing blocking information

- constants (cos36(), sin36(), cos72(), two(), one(), sin72(), sin60(), half(), pi()): module containing constants and parameters used in the code.
- truncation: This module defines the grid points and the truncation

Variables

- fft/ni [integer,private/parameter=100]
- fft/nd[integer,private]
- fft/d_fft_init(:)[real,private/allocatable]
- fft/i_fft_init (100) [integer,private]

Subroutines and functions

```
subroutine fft/init fft(n)
```

Purpose of this subroutine is to calculate and store several values that will be needed for a fast fft

```
transform. The actual transform is performed by the subroutine fftJW.
         Parameters n [integer,in]:: Dimension of problem, number of grid points
         Called from horizontal ()
         Call to abortrun(), factorise()
subroutine fft/finalize_fft()
         Called from finalize_horizontal_data()
subroutine fft/fft_to_real(f, ld_f, nrep)
         Parameters
               • f (ld_f,nrep) [real,inout]
              • ld f [integer, in, ]
              • nrep [integer,in,]
         Called from getdvptr()
         Call to fft jw()
subroutine fft/fft thetab(f, dir)
         Parameters
              • f (nrp,nfs) [real,inout]
               • dir [integer,in] :: back or forth transform
         Called from fields average().
                                            graphout_ic(),
                                                                get_bpol(), initv(),
             inits(), get_btor(),
                                            initxi(),
                                                          1m2pt(),
                                                                       get_br_v_bcs(),
             transform_to_grid_space(), transform_to_lm_space(), get_dtblm(),
             store_movie_frame_ic(), get_b_surface()
         Call to fft jw()
```

subroutine fft/**fftjw**(a, ld_a, n, isign, nsize, wrk, wd1, wd2, i_fft_init, d_fft_init)

The routines has been adopted by Gary Glatzmaier and has subsequently been modified by Uli Christensen and Johannes Wicht

It performs a number of simultaneous real/half-complex periodic fast fourier transforms or corresponding inverse transforms, using ordinary spatial order of gridpoint values. given a set of real data vectors, the package returns a set of "half-complex" fourier coefficient vectors, or vice versa. the length of the transforms must be an even number that has no other factors except possibly powers of 2, 3, and 5. this version of fft991 is optimized for use on the cray-1.

on input a(ld a,*)

an array of length (ld_a,nsize) containing the input data or coefficient vectors. This array is overwritten by the results.

n the length of each transform (see definition of transforms, below).

nsize the number of transforms to be done simultaneously.

isign

- **= +1 for a transform from fourier coefficients to** gridpoint values.
- = -1 for a transform from gridpoint values to fourier coefficients.

on output a if isign = +1, and n_theta_max coefficient vectors are supplied each containing the sequence

```
a(0),b(0),a(1),b(1),...,a(n/2),b(n/2) (n+2 values)
```

then the result consists of n_theta_max data vectors each containing the corresponding n+2 gridpoint values

```
for fft991, x(0), x(1), x(2),...,x(n-1),0,0. (n+2) real values with x(n)=x(n+1)=0
```

when isign = +1, the transform is defined by x(j)=sum(k=0,...,n-1)(c(k)*exp(2*i*j*k*pi/n)) where c(k)=a(k)+i*b(k) and c(n-k)=a(k)-i*b(k) and i=sqrt(-1) for k=0,...,n/2 i.e., (n/2+1) complex values with c(0)=c(n)=a(0) and c(n/2)=a(n/2)=0

if isign = -1, and n_theta_max data vectors are supplied each containing a sequence of gridpoint values x(j) as defined above, then the result consists of n_theta_max vectors each containing the corresponding fourier cofficients a(k), b(k), $0 \le k$. le n/2.

```
when isign = -1, the inverse transform is defined by c(k)=(1/n)*sum(j=0,...,n-1)(x(j)*exp(-2*i*j*k*pi/n)) where c(k)=a(k)+i*b(k) and i=sqrt(-1) for k=0,...,n/2
```

a call with isign=+1 followed by a call with isign=-1 (or vice versa) returns the original data.

note the fact that the gridpoint values x(j) are real implies that b(0)=b(n/2)=0. for a call with isign=+1, it is not actually necessary to supply these zeros. note starting from grid with x(n)=x(n+1)=0 then transforming to spectral (sign=-1) then c(n/2)=a(n/2) is not necessarily 0 unless there is no aliasing.

- a (ld_a,*) [real,inout] :: fields to be transformed
- ld_a [integer,in,] :: leading dimension of a
- **n** [integer,in] :: dimension of problem
- **isign** [integer,in] :: back/forth transform for isign=1/-1
- **nsize** [integer,in] :: number of fields for

```
• wrk (wd1,wd2) [real,inout] :: work array
                 • wd1 [integer,in,]
                 • wd2 [integer,in,]
                 • i_fft_init (*) [integer,in] :: factorization information from init_fft
                 • d_fft_init (*) [real,in] :: trigonometric functions from init_fft
           Called from fft_thetab(), fft_to_real()
           Call to abortrun(), fft99ajw(), wpass2jw(), wpass3jw(), wpass4jw(),
               wpass5jw(), fft99bjw()
subroutine fft/fft99ajw(a, work, trigs, nrp, nsize)
           Parameters
                 • a (*) [real,inout]
                 • work (*) [real,inout]
                 • trigs (*) [real,in]
                 • nrp [integer,in]
                 • nsize [integer,in]
           Called from fftjw()
subroutine fft/fft99bjw(work, a, trigsf, nrp, nsize)
           postprocessing step (isign=-1) (gridpoint to spectral transform)
           Parameters
                 • work (*) [real,inout]
                 • a (*) [real, inout]
                 • trigsf (*) [real,in]
                 • nrp [integer,in]
                 • nsize [integer,in]
           Called from fftjw()
subroutine fft/wpass2jw(a, b, c, d, trigs, nrp, nsize)
           reduction for factor 2
           Parameters
                 • a (*) [real,in]
                 • b (*) [real,in]
                 • c (*) [real,out]
                 • d (*) [real,out]
                 • trigs (*) [real,in]
                 • nrp [integer,in]
```

• **nsize** [integer,in]

```
Called from fft jw()
\verb"subroutine" fft/\verb"wpass3jw" (a,b,c,d,trigs,nrp,la,nsize)
           called in fftJW
           Parameters
                  • a (*) [real,in]
                  • b (*) [real,in]
                  • c (*) [real,out]
                  • d (*) [real,out]
                  • trigs (*) [real,in]
                  • nrp [integer,in]
                  • la [integer,in]
                  • nsize [integer,in]
           Called from fftjw()
           Call to abortrun()
subroutine fft/wpass4jw(a, b, c, d, trigs, nrp, la, nsize)
           called in fftJW reduction for factor 4
           Parameters
                  • a (*) [real,in]
                  • b (*) [real,in]
                  • c (*) [real,out]
                  • d (*) [real,out]
                  • trigs (*) [real,in]
                  • nrp [integer,in]
                  • la [integer,in]
                  • nsize [integer,in]
           Called from fftjw()
           Call to abortrun()
subroutine fft/wpass5jw(a, b, c, d, trigs, nrp, la, nsize)
           called in fftJW reduction for factor 5
           Parameters
                  • a (*) [real,in]
                  • b (*) [real,in]
                  • c (*) [real,out]
```

• **d** (*) [real,out]

```
• trigs (*) [real,in]
```

- **nrp** [integer,in]
- la [integer,in]
- nsize [integer,in]

Called from fftjw()

Call to abortrun()

10.12 Linear algebra

10.12.1 algebra.f90

Quick access

Needed modules

- precision_mod: This module controls the precision used in MagIC
- omp_lib
- useful (abortrun ()): library with several useful subroutines
- constants (one ()): module containing constants and parameters used in the code.

Variables

- algebra/solve_mat [public]
- algebra/zero_tolerance [real,private/parameter=1.0e-15_cp]

Subroutines and functions

```
subroutine algebra/solve_mat_complex_rhs(a, ia, n, ip, bc1)
```

This routine does the backward substitution into a lu-decomposed real matrix a (to solve a * x = bc1) were bc1 is the right hand side vector. On return x is stored in bc1.

- a (ia,*) [real,in] :: real n X n matrix
- ia [integer,in,] :: first dim of a
- **n** [integer,in] :: dimension of problem
- ip (*) [integer,in] :: pivot pointer of legth n
- **bc1** (*) [complex,inout] :: on input RHS of problem

subroutine algebra/**solve_mat_complex_rhs_multi**(a, ia, n, ip, bc, nrhss)

This routine does the backward substitution into a lu-decomposed real matrix a (to solve a * x = bc) simultaneously for nRHSs complex vectors bc. On return the results are stored in the bc.

Parameters

- a (ia,n) [real,in] :: real n X n matrix
- ia [integer, in,] :: leading dimension of a
- **n** [integer,in,] :: dimension of problem
- ip (n) [integer,in] :: pivot pointer of length n
- **bc** (,) [complex,inout]
- **nrhss** [integer,in] :: number of right-hand sides

```
\verb|subroutine| algebra/\verb|solve_mat_real_rhs| (a, ia, n, ip, b)
```

like the linpack routine backward substitution of vector b into lu-decomposed matrix a to solve a * x = b for a single real vector b

sub sgefa must be called once first to initialize a and ip

a: (input) nxn real matrix n: (input) size of a and b ip: (input) pivot pointer array of length n b: (in/output) rhs-vector on input, solution on output

Parameters

- **a** (ia,*) [real,in]
- ia [integer,in,] :: first dim of a
- **n** [integer,in] :: dim of problem
- **ip** (*) [integer,in] :: pivot information
- **b** (*) [real,inout]

subroutine algebra/prepare_mat (a, ia, n, ip, info)

like the linpack routine

lu decomposes the real matrix a(n,n) via gaussian elimination

a: (in/output) real nxn matrix on input, lu-decomposed matrix on output ia: (input) first dimension of a (must be >= n) n: (input) 2nd dimension and rank of a ip: (output) pivot pointer array info: (output) error message when /= 0

- a (ia,*) [real,inout]
- ia [integer,in,]
- **n** [integer,in]
- **ip** (*) [integer,out] :: pivoting information
- info [integer,out]

```
Called from get_p0mat(), get_s0mat(), inits(), initxi(), get_wpsmat(),
    get_zmat(), pt_cond(), get_wptmat(), get_wmat(), get_ps0mat(),
    xi_cond(), get_pt0mat(), ps_cond(), get_wpmat(), j_cond(), get_bmat(),
    get_smat(), getbackground(), get_ximat(), get_xi0mat(), get_z10mat()
Call to abortrun()
```

10.13 Radial derivatives and integration

10.13.1 radial_derivatives.f90

Description

Radial derivatives functions

Quick access

```
Variables get_dcheb, get_dr, work_1d_real
Routines finalize_der_arrays(), get_dddcheb(), get_dddr(), get_ddcheb(),
    get_ddr(), get_dcheb_complex(), get_dr_complex(), get_dcheb_real_1d(),
    get_dr_real_1d(), initialize_der_arrays()
```

Needed modules

- mem_alloc: This little module is used to estimate the global memory allocation used in MagIC
- cosine_transform_odd
- radial_scheme (type_rscheme()): This is an abstract type that defines the radial scheme used in MagIC
- precision_mod: This module controls the precision used in MagIC
- logic(l_finite_diff()): Module containing the logicals that control the run
- constants (zero(), three(), one()): module containing constants and parameters used in the code.

Variables

- radial_der/get_dcheb [public]
- radial_der/get_dr [public]
- radial_der/work (:,:) [complex,private/allocatable]
- radial_der/work_1d_real (:) [real,private/allocatable]

Subroutines and functions

```
subroutine radial_der/initialize_der_arrays (n_r_max, llm, ulm)
Allocate work arrays to compute derivatives
```

Parameters

- n_r_max [integer,in]
- **llm** [integer,in]
- ulm [integer,in]

Called from magic

```
subroutine radial_der/finalize_der_arrays()
    Deallocate work arrays
```

Called from magic

Returns Chebyshev coeffitients of first derivative df and second derivative ddf for a function whose cheb-coeff. are given as columns in array f(n_f_max,n_r_max).

Parameters

- **f** (n_f_max,n_r_max) [complex,in]
- **df** (n_f_max,n_r_max) [complex,out]
- **n_f_max** [integer,in,] :: Max no of functions
- n_f_start [integer,in] :: No of function to start with
- **n_f_stop** [integer,in] :: No of function to stop with
- **n_r_max** [integer,in,] :: second dimension of f,df,ddf
- **n_cheb_max** [integer,in] :: Number of cheb modes
- **d_fac** [real,in] :: factor for interval mapping

subroutine radial_der/get_dcheb_real_ld(f, df, n_r_max, n_cheb_max, d_fac)

Parameters

- **f** (n_r_max) [real,in]
- **df** (*n_r_max*) [real,out]
- **n_r_max** [integer,in,] :: Dimension of f,df,ddf
- n_cheb_max [integer,in] :: Number of cheb modes
- **d_fac** [real,in] :: factor for interval mapping

```
subroutine radial_der/get_ddcheb (f, df, ddf, n\_f\_max, n\_f\_start, n\_f\_stop, n\_r\_max, n\_cheb\_max, d\_fac)
```

Returns Chebyshev coefficients of first derivative df and second derivative ddf for a function whose cheb-coeff. are given as columns in array f(n_c_tot,n_r_max).

- **f** (n_f_max,n_r_max) [complex,in]
- \mathbf{df} (n_f_max,n_r_max) [complex,out]
- **ddf** (n_f_max,n_r_max) [complex,out]
- n_f_max [integer,in,] :: First dimension of f,df,ddf

- **n_f_start** [integer, in] :: No of column to start with
- **n_f_stop** [integer,in] :: No of column to stop with
- n_r_max [integer,in,] :: second dimension of f,df,ddf
- n_cheb_max [integer,in] :: Number of cheb modes
- **d** fac [real,in] :: factor for interval mapping

Called from get ddr()

Returns chebychev coeffitiens of first derivative df and second derivative ddf for a function whose cheb-coeff. are given as columns in array $f(n_c_{tot}, n_r_{tot})$.

Parameters

- \mathbf{f} (n_f_max,n_r_max) [complex,in]
- **df** (n_f_max,n_r_max) [complex,out]
- **ddf** (n_f_max,n_r_max) [complex,out]
- **dddf** (n_f_max,n_r_max) [complex,out]
- **n_f_max** [integer,in,] :: First dimension of f,df,ddf
- n_f_start [integer,in] :: No of column to start with
- **n_f_stop** [integer,in] :: No of column to stop with
- **n_r_max** [integer,in,] :: second dimension of f,df,ddf
- n_cheb_max [integer,in] :: Number of cheb modes
- **d_fac** [real,in] :: factor for interval mapping

Called from get_dddr()

```
subroutine radial_der/get_dr_real_1d(f, df, n_r_max, r_scheme)
```

Parameters

- **f** (*n*_*r*_*max*) [real,in]
- **df** (*n_r_max*) [*real,out*] :: first derivative of f
- **n_r_max** [integer,in,] :: number of radial grid points
- r_scheme [real]

Returns first radial derivative df of the input function f. Array $f(n_f_max,^*)$ may contain several functions numbered by the first index. The subroutine calculates the derivaties of the functions $f(n_f_start,^*)$ to $f(n_f_stop)$ by transforming to a Chebychev representation using n_r_max radial grid points .

- **f** (n_f_max,n_r_max) [complex,inout]
- **df** (n_f_max,n_r_max) [complex,out] :: first derivative of f

- n_f_max [integer,in,] :: first dim of f
- **n f start** [integer,in] :: first function to be treated
- n_f_stop [integer,in] :: last function to be treated
- n_r_max [integer,in,] :: number of radial grid points
- r scheme [real]

Options

- **nocopy** [logical,in,optional]
- l_dct_in [logical,in,optional]

```
subroutine radial_der/get_ddr(f, df, ddf, n\_f\_max, n\_f\_start, n\_f\_stop, n\_r\_max, r\_scheme[, l\_dct\_in[)
```

Returns first radial derivative df and second radial derivative ddf of the input function f. Array $f(n_f_max,*)$ may contain several functions numbered by the first index. The subroutine calculates the derivatives of the functions $f(n_f_start,*)$ to $f(n_f_stop)$ by transforming to a Chebychev representation using n_r_max radial grid points.

Parameters

- \mathbf{f} (n_f_max,n_r_max) [complex,in]
- **df** (n_f_max,n_r_max) [complex,out] :: first derivative of f
- **ddf** (n_f_max,n_r_max) [complex,out] :: second derivative of f
- **n f max** [integer,in,] :: first dim of f
- **n_f_start** [integer,in] :: first function to be treated
- **n_f_stop** [integer,in] :: last function to be treated
- n_r_max [integer,in,] :: number of radial grid points
- r scheme [real]

Options l_dct_in [logical,in,optional]

```
Called from getstartfields(), updateb(), updates(), updatexi(),
    updatewpt(), updatewps(), updatez(), updatewp(), updates_ala()
```

Call to get_ddcheb()

Returns first radial derivative df, the second radial deriv. ddf, and the third radial derivative dddf of the input function f. Array $f(n_f_max,^*)$ may contain several functions numbered by the first index. The subroutine calculates the derivatives of the functions $f(n_f_start,^*)$ to $f(n_f_start)$ by transforming to a Chebychev representation using n_r_max radial grid points.

- **f** (n_f_max,n_r_max) [complex,in]
- **df** (n f max, n r max) [complex, out] :: first derivative of f
- **ddf** (n_f_max,n_r_max) [complex,out] :: second derivative of f
- **dddf** (n_f_max,n_r_max) [complex,out] :: third derivative of f

```
n_f_max [integer,in,] :: first dim of f
n_f_start [integer,in] :: first function to be treated
n_f_stop [integer,in] :: last function to be treated
n_r_max [integer,in,] :: number of radial grid points
r_scheme [real]
Options l_dct_in [logical,in,optional]
Called from updatewpt(), updatewps(), updatewp()
```

10.13.2 radial_derivatives_even.f90

Call to get_dddcheb()

Quick access

```
Routines get_ddcheb_even(), get_ddrns_even(), get_dcheb_even(), get_drns_even()
```

Needed modules

- precision_mod: This module controls the precision used in MagIC
- cosine_transform_odd
- cosine_transform_even
- constants (zero ()): module containing constants and parameters used in the code.

Variables

Subroutines and functions

Returns first rarial derivative df and second radial derivative ddf of the input function f. Array $f(n_f_max,^*)$ may contain several functions numbered by the first index. The subroutine calculates the derivaties of the functions $f(n_f_start,^*)$ to $f(n_f_start)$ by transforming to a Chebychev representation using n_r_max radial grid points. The cheb transforms have to be initialized by calling init_costf1 and init_costf2.

- \mathbf{f} (n_f_max,n_r_max) [complex,in]
- **df** (n f max, n r max) [complex, out] :: first derivative of f
- **ddf** (n_f_max,n_r_max) [complex,out] :: second derivative of f
- n_f_max [integer,in,] :: first dim of f
- **n f start** [integer,in] :: first function to be treated

chebt_odd,

```
• n_f_stop [integer,in] :: last function to be treated
                 • n_r_max [integer,in,] :: number of radial grid points
                 • n_cheb_max [integer,in] :: number of cheb modes
                 • dr_fac [real,in] :: mapping factor
                 • work1 (n f max, n r max) [complex, out] :: work array needed for costf
                 • work2 (n f max, n r max) [complex, out] :: work array needed for costf
                 • chebt_odd [costf_odd_t,in]
                 • chebt_even [costf_even_t,in]
           Called from getstartfields(), updateb()
           Call to get_ddcheb_even()
subroutine radial_der_even/get_drns_even(f, df, n_f_max, n_f_start, n_f_stop, n_r_max,
                                                         n_{cheb_{max}}
                                                                       dr_fac, work1,
                                                         chebt even)
           Returns first rarial derivative df and second radial derivative ddf of the input function f. Array
           f(n f max,*) may contain several functions numbered by the first index. The subroutine calculates
           the derivaties of the functions f(n f start,*) to f(n f stop) by transforming to a Chebychev repre-
```

Parameters

init costf1 and init costf2.

- \mathbf{f} (n f max, n r max) [complex, inout]
- **df** (n_f_max,n_r_max) [complex,out] :: first derivative of f
- n_f_max [integer,in,] :: first dim of f
- **n_f_start** [integer,in] :: first function to be treated
- **n_f_stop** [integer,in] :: last function to be treated
- n_r_max [integer,in,] :: number of radial grid points
- n_cheb_max [integer,in] :: number of cheb modes
- **dr fac** [real,in] :: mapping factor
- work1 (n f max, n r max) [complex, out] :: work array needed for costf

sentation using n_r_max radial grid points. The cheb transforms have to be initialized by calling

- chebt_odd [costf_odd_t,in]
- chebt_even [costf_even_t,in]

```
Called from fields average(), write dtb frame()
Call to get_dcheb_even()
```

```
subroutine radial_der_even/get_ddrns_even(f, df, ddf, n_f_max, n_f_start, n_f_stop,
                                                n_r_max,
                                                         n_cheb_max, dr_fac,
                                                chebt_odd, chebt_even)
```

Returns first rarial derivative df and second radial derivative ddf of the input function f. Array f(n_f_max,*) may contain several functions numbered by the first index. The subroutine calculates the derivaties of the functions $f(n_f_start,^*)$ to $f(n_f_stop)$ by transforming to a Chebychev representation using n_r_m radial grid points. The cheb transforms have to be initialized by calling init costf1 and init costf2.

Parameters

```
• f (n_f_max,n_r_max) [complex,inout]
```

- **df** (n_f_max,n_r_max) [complex,out] :: first derivative of f
- **ddf** (n_f_max,n_r_max) [complex,out] :: second derivative of f
- n_f_max [integer,in,] :: first dim of f
- n_f_start [integer,in] :: first function to be treated
- **n_f_stop** [integer,in] :: last function to be treated
- n_r_max [integer,in,] :: number of radial grid points
- n_cheb_max [integer,in] :: number of cheb modes
- **dr_fac** [real,in] :: mapping factor
- work1 (n_f_max,n_r_max) [complex,out] :: work array needed for costf
- **chebt_odd** [costf_odd_t,in]
- chebt_even [costf_even_t,in]

```
Called from fields average()
```

Call to get_ddcheb_even()

```
subroutine radial_der_even/get_dcheb_even(f, df, n\_f\_max, n\_f\_start, n\_f\_stop, n\_r\_max, n\_cheb\_max, d\_fac)
```

Returns Chebyshev coefficients of first derivative df and second derivative ddf for a function whose cheb-coeff. are given as columns in array $f(n_f_max,n_r_max)$.

Parameters

- \mathbf{f} (n_f_max,n_r_max) [complex,in]
- \mathbf{df} (n_f_max,n_r_max) [complex,out]
- **n_f_max** [integer,in,] :: First dimension of f,df
- n_f_start [integer,in] :: No of function to start with
- **n_f_stop** [integer,in] :: No of function to stop with
- **n_r_max** [integer,in,] :: second dimension of f,df
- **n_cheb_max** [integer,in] :: Number of cheb modes
- **d_fac** [real,in] :: factor for interval mapping

Called from get_drns_even()

Returns Chebyshev coefficients of first derivative df and second derivative ddf for a function whose cheb-coeff. are given as columns in array f(n_f_max,n_r_max).

- \mathbf{f} (n_f_max,n_r_max) [complex,in]
- **df** (n_f_max,n_r_max) [complex,out]
- **ddf** (n_f_max,n_r_max) [complex,out]
- **n_f_max** [integer,in,] :: First dimension of f,df,ddf
- n_f_start [integer,in] :: No of function to start with
- **n_f_stop** [integer,in] :: No of function to stop with
- n_r_max [integer,in,] :: second dimension of f,df,ddf
- n_cheb_max [integer,in] :: Number of cheb modes
- **d_fac** [real,in] :: factor for interval mapping

Called from get_ddr_even(), get_ddrns_even()

10.13.3 integration.f90

Description

Radial integration functions

Quick access

```
Routines rintic(), rint_r()
```

Needed modules

- precision_mod: This module controls the precision used in MagIC
- cosine_transform_odd
- radial_scheme (type_rscheme()): This is an abstract type that defines the radial scheme used in MagIC
- constants (one (), two (), half ()): module containing constants and parameters used in the code.

Variables

Subroutines and functions

function integration/rintic(f, nrmax, drfac, chebt)

This function performs the radial integral over a function f that is given on the appropriate nRmax radial Chebychev grid points.

- **f** (nrmax) [real,inout]
- nrmax [integer, in,]
- drfac [real,in]
- **chebt** [costf_odd_t,in]

```
Return rintic [real]
```

```
Called from get_power(), get_e_mag(), spectrum()
```

```
function integration/rint_r (f, r, r_scheme)
```

Same as function rInt but for a radial dependent mapping function dr_fac2.

Parameters

- **f** (*) [real,in]
- **r** (*) [real,in]
- **r_scheme** [real] :: Radial scheme (FD or Cheb)

Return rint [real]

```
Called from dtvrms(), outto(), get_angular_moment(), get_power(),
  outheat(), get_amplitude(), get_poltorrms(), get_e_mag(), updatewp(),
  dtbrms(), get_u_square(), spectrum(), getdlm(), outhelicity(),
  get_e_kin(), output(), outperppar(), precalc(), spectrum_temp()
```

10.14 Blocking and LM mapping

10.14.1 blocking.f90

Description

Module containing blocking information

Quick access

```
Variables get_theta_blocking, nfs, nlmbs, nthetabs, sizelmb, sizethetab, nbsave, sizethetabi, cacheblock_size_in_b, nbdown, lmstartb, lmstopb, 12lmas, 1m21, 1m2lma, 1m2lmp, 1m2lms, 1m2m, 1m2mc, 1mp2l, 1mp2lm, 1mp2lmpa, 1mp2lmps, nlmbs2, 1m2, 1mp2, sizelmb2, 1m221, 1m22lm, 1m22m, 1o_map, 1o_sub_map, sn_sub_map, st_map, st_sub_map
```

```
Routines initialize_blocking(), finalize_blocking(), get_lorder_lm_blocking(), get_snake_lm_blocking(), get_standard_lm_blocking(), get_subblocks(), get_theta_blocking_cache(), get_theta_blocking_openmp()
```

Needed modules

- mem_alloc (memwrite(), bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (abortrun(), logwrite()): library with several useful subroutines
- output_data (n_log_file(), log_file()): This module contains the parameters for output control
- precision mod: This module controls the precision used in MagIC

- parallel_mod(n_procs(), rank_with_l1m0(), nthreads(), rank(), nlmbs_per_rank()): This module contains the blocking information
- logic(l_finite_diff(), l_save_out()): Module containing the logicals that control the run
- lmmapping (mappings(), deallocate_mappings(), subblocks_mappings(), deallocate_subblocks_mappings(), allocate_subblocks_mappings())
- constants (one ()): module containing constants and parameters used in the code.
- truncation (l_max(), minc(), lmp_max(), l_axi(), n_r_max(), m_max(), lm_max(), nrp(), n_theta_max()): This module defines the grid points and the truncation

Variables

- blocking/**nbsave** [integer,private/parameter=16]
- blocking/lmstartb(:)[integer,allocatable/public]
- blocking/lm2 (:,:) [integer,pointer/public]
- blocking/lmp2 (:,:) [integer,pointer/public]
- blocking/lm2lms (:) [integer, pointer/public]
- blocking/lmp21 (:) [integer, pointer/public]
- blocking/lm221 (:,:,:) [integer,pointer/public]
- blocking/lm22m(:,:,:) [integer,pointer/public]
- blocking/lmp2lm(:)[integer,pointer/public]
- blocking/lm2lmp(:)[integer,pointer/public]
- blocking/get_theta_blocking[public]
- blocking/lo_sub_map [subblocks_mappings,target/public]
- blocking/lmp2lmps (:) [integer, pointer/public]
- blocking/nthetabs [integer, public]
- blocking/sn_sub_map [subblocks_mappings,target/public]
- blocking/lm2m(:)[integer,pointer/public]
- blocking/lm21(:)[integer,pointer/public]
- blocking/lmp2lmpa (:) [integer, pointer/public]
- blocking/lm2mc(:) [integer,pointer/public]
- blocking/nlmbs[integer,public]
- blocking/sizethetab[integer,public]
- blocking/st_map [mappings,target/public]
- blocking/lo_map [mappings,target/public]
- blocking/nlmbs2 (:) [integer,pointer/public]
- blocking/sizelmb[integer,public]
- blocking/sizethetabi[integer,private/parameter=284]

```
• blocking/lm22lm(:,:,:) [integer,pointer/public]
   • blocking/nfs [integer,public]
   • blocking/lmstopb(:)[integer,allocatable/public]
   • blocking/121mas (:) [integer,pointer/public]
   • blocking/cacheblock size in b[integer, public]
   • blocking/nbdown [integer, private/parameter=8]
   • blocking/lm2lma(:) [integer,pointer/public]
   • blocking/sizelmb2 (:,:) [integer,pointer/public]
   • blocking/st_sub_map[subblocks_mappings,target/public]
Subroutines and functions
subroutine blocking/initialize_blocking()
         Called from magic
         Call to allocate_mappings(),
                                                 logwrite(),
                                                                          abortrun(),
            get_standard_lm_blocking(),
                                                           get_snake_lm_blocking(),
            get_lorder_lm_blocking(),
                                                   allocate_subblocks_mappings(),
                                                        get theta blocking cache(),
            get subblocks(),
            get_theta_blocking_openmp(), memwrite()
subroutine blocking/finalize_blocking()
         Called from magic
         Call to deallocate_mappings(), deallocate_subblocks_mappings()
subroutine blocking/get_subblocks(map, sub_map)
         Parameters
              • map [mappings,in]
              • sub map [subblocks mappings,inout]
         Called from initialize blocking()
         Call to abortrun()
subroutine blocking/get_standard_lm_blocking(map, minc)
         Parameters
              • map [mappings,inout]
              • minc [integer,in]
```

Called from initialize_blocking()

Call to abortrun()

subroutine blocking/get_lorder_lm_blocking(map, minc)

- map [mappings,inout]
- minc [integer,in]

Called from initialize_blocking()

Call to abortrun()

Parameters

- n_theta_max [integer,in]
- **nrp** [integer,in]
- cacheblock_size_in_b [integer,in]
- **nthetabs** [integer,out]
- **sizethetab** [integer,out]

Called from initialize_blocking()

subroutine blocking/get_theta_blocking_openmp(n_theta_max, nthreads, nthetabs, sizethetab)

This routine determines the number of theta blocks and the blocksize with respect to the number of threads.

Parameters

- n_theta_max [integer,in]
- **nthreads** [integer,in]
- **nthetabs** [integer,out]
- sizethetab [integer,out]

Called from initialize_blocking()

10.14.2 LMmapping.f90

Quick access

```
Routines deallocate_mappings(), deallocate_subblocks_mappings(), allocate_mappings(), allocate_subblocks_mappings()
```

Needed modules

- precision_mod: This module controls the precision used in MagIC
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC

• truncation (1_axi ()): This module defines the grid points and the truncation

Types

• type lmmapping/unknown_type

Type fields

- % 1_max [integer]
- % lm2mc (*) [integer, allocatable]
- % lm2 (,) [integer, allocatable]
- % m_max [integer]
- % lmp21 (*) [integer,allocatable]
- % lmp2m (*) [integer,allocatable]
- % lmp_max [integer]
- % lmp2lm (*) [integer, allocatable]
- % lmp2 (,) [integer, allocatable]
- % lm_max [integer]
- % lmp2lmps (*) [integer,allocatable]
- % lm2lms (*) [integer, allocatable]
- % lm2lmp (*) [integer,allocatable]
- % lm2m (*) [integer,allocatable]
- % lm21 (*) [integer,allocatable]
- % 121mas (*) [integer, allocatable]
- % lmp2lmpa (*) [integer,allocatable]
- % lm2lma (*) [integer, allocatable]
- type lmmapping/unknown_type

Type fields

- % 1_max [integer]
- % sizelmb2max [integer]
- % nlmbs [integer]
- % lm22lm (,,*) [integer,allocatable]
- % lm221 (,,*) [integer,allocatable]
- % lm22m (,,*) [integer, allocatable]
- % sizelmb2 (,) [integer, allocatable]
- % m_max [integer]
- % nlmbs2 (*) [integer, allocatable]

Variables

Subroutines and functions

```
subroutine lmmapping/allocate_mappings (self, l_max, lm_max, lmp_max)
```

Parameters

- **self** [mappings]
- l_max [integer,in]
- lm_max [integer,in]
- lmp_max [integer,in]

Called from initialize_blocking()

subroutine lmmapping/deallocate_mappings(self)

Parameters self [mappings]

Called from finalize blocking()

subroutine lmmapping/allocate_subblocks_mappings (self, map, nlmbs, l_max, lmstartb, lmstopb)

Parameters

- **self** [subblocks_mappings]
- map [mappings,in]
- nlmbs [integer,in,]
- l_max [integer,in]
- **Imstartb** (*nlmbs*) [integer,in]
- **Imstopb** (*nlmbs*) [integer,in]

Called from initialize_blocking()

subroutine lmmapping/deallocate_subblocks_mappings (self)

Parameters self [subblocks_mappings]

Called from finalize_blocking()

10.15 IO: time series, radial profiles and spectra

10.15.1 output.f90

Quick access

Variables n_cmb_file, n_cmb_setsmov, n_cmbmov_file, n_dt_cmb_file, n_dt_cmb_file, n_dt_cmb_sets, n_dte_file, n_e_sets, n_par_file, n_spec, nbpotsets, nlogs, npvsets, nrms_sets, ntomovsets, ntormssets, ntosets, ntpotsets, nvpotsets, cmb_file, cmbmov_file, dt_cmb_file, dte_file, par_file, dteint, e_kin_pmean, e_kin_tmean, e_mag_pmean, e_mag_tmean, etot, etotold, timenormlog, timenormrms, timepassedlog, timepassedrms, n_b_r_file,

```
n\_b\_r\_sets, n\_t\_r\_file, n\_t\_r\_sets, n\_v\_r\_file, n\_v\_r\_sets, dipcmbmean, dipmean, dlbmean, dlvcmean, dlvmean, dmbmean, dmvmean, dpvmean, dzvmean, elcmbmean, elmean, geosmean, lbdissmean, lvdissmean, rmmean, rolmean, b\_r\_file, t\_r\_file, v\_r\_file, bicb
```

Routines finalize_output(), initialize_output(), output()

Needed modules

- horizontal_data (hdif_b(), dpl0eq(), dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- movie_data(movie_gather_frames_to_rank0())
- useful (logwrite()): library with several useful subroutines
- rms (dtvrms (), zerorms (), dtbrms ()): This module contains the calculation of thr RMS force balance and induction terms.
- lmloop_data(llmmag(), lm_per_rank(), lm_on_last_rank(), ulm(), llm(), ulmmag())
- radial_spectra
- getdlm_mod (getdlm()): This module is used to calculate the lengthscales
- precision_mod: This module controls the precision used in MagIC
- graphout_mod (graphout_ic()): This module contains the subroutines that store the 3-D graphic files.
- magnetic_energy (get_e_mag())
- integration (rint_r()): Radial integration functions
- parallel_mod: This module contains the blocking information
- num_param (escale (), tscale ()): Module containing numerical and control parameters
- out_movie_ic(store_movie_frame_ic())
- physical_parameters (prmag(), lffac(), ek(), ktopv(), nvarcond(), opm(), ekscaled()): Module containing the physical parameters
- radial_functions (rscheme_oc(), orhol(), r_cmb(), or2(), or1(), r(), r_icb(), sigma()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- output_data(l_max_cmb(), n_r_step(), n_log_file(), l_max_r(), n_coeff_r(), tag(), log_file(), n_coeff_r_max(), n_r_array()): This module contains the parameters for output control
- power (get_power())
- logic (l_hel(), lverbose(), l_pv(), l_rmagspec(), l_mag_lf(), l_perppar(), l_sric(), l_mag(), l_non_rot(), l_r_fieldt(), l_average(), l_cond_ic(), l_movie(), l_anel(), l_heat(), l_cmb_field(), l_chemical_conv(), l_movie_ic(), l_store_frame(), l_power(), l_r_field(), l_dtb(), l_par(), l_save_out(), l_rms(), l_dt_cmb_field(), l_energy_modes()): Module containing the logicals that control the run
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- storecheckpoints: This module contains several subroutines that can be used to store the checkpoint_#.tag files

- kinetic_energy (get_e_kin(), get_u_square())
- out_coeff (write_pot(), write_coeff_r(), write_bcmb()): This module contains the subroutines that calculate the Bcmb files, the [BIVIT]_coeff_r files and the [BIVIT]_lmr files
- omega (outomega ()): This module allows to compute the axisymmetric zonal flow versus the cylindrical radius s. By
- blocking (lm2(), st_map(), lo_map()): Module containing blocking information
- constants (surf_cmb(), two(), three(), mass(), vol_oc(), vol_ic()): module containing constants and parameters used in the code.
- truncation (n_r_ic_max(), l_max(), minc(), l_maxmag(), n_r_max(), lm_max(), n r maxmag()): This module defines the grid points and the truncation
- fieldslast (dbdt_iclast_lmloc(), dzdtlast_lo(), djdtlast_lmloc(), djdt_iclast_lmloc(), dpdtlast_lmloc(), dxidtlast_lmloc(), dwdtlast_lmloc(), dsdtlast_lmloc(), dbdtlast_lmloc()): This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- outrot(write rot())
- geos_mod (outpv(), getegeos()): This module is used to calculate the outputs when either l_par or 1 PV are set to .true.
- out_movie(write_movie_frame())
- fields (aj_lmloc(), ddj_ic(), aj_ic(), ddw_lmloc(), ddb_ic(), b_lmloc(), dj_lmloc(), ddj_ic_lmloc(), db_lmloc(), s_lmloc(), ddb_lmloc(), b_ic(), ds_lmloc(), ddb_ic_lmloc(), p_lmloc(), dxi_lmloc(), db_ic_lmloc(), dw_lmloc(), dp_lmloc(), dj_ic_lmloc(), dj_ic(), aj_ic_lmloc(), omega_ic(), z_lmloc(), omega_ma(), w_lmloc(), b_ic_lmloc(), ddj_lmloc(), xi_lmloc(), dz_lmloc(): This module contains the potential fields and their radial derivatives
- spectra(get_amplitude(), spectrum(), spectrum_temp())
- dtb_mod (get_dtblmfinish()): This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output....
- outmisc_mod (outhelicity(), outheat()): This module contains several subroutines that can compute and store various informations: helicity, heat transfer.
- radial_data (n_r_cmb(), n_r_icb(), nrstopmag(), nrstartmag(), nrstop(), nrstart()): This module defines the MPI decomposition in the radial direction.
- communications (gather_all_from_lo_to_rank0(), gt_ic(), gather_from_lo_to_rank0(), gt_oc())
- outpar_mod (outpar(), outperppar()): This module is used to compute several time-averaged radial profiles: fluxes, boundary layers, etc.
- outto_mod(outto())
- fields_average_mod (fields_average()): This module is used when one wants to store time-averaged quantities

- output_mod/dlvmean [real,private/save]
- output_mod/nbpotsets[integer,private]

- output_mod/ntpotsets[integer,private]
- output_mod/etot [real,private]
- output_mod/bicb(:) [complex,private/allocatable]
- output_mod/ntosets[integer,private]
- output mod/n dte file [integer, private]
- output mod/timepassedlog[real,private]
- output_mod/n_par_file [integer,private]
- output_mod/n_cmbmov_file [integer,private]
- output_mod/t_r_file(:)[character,private/allocatable]
- output_mod/**dpvmean** [real,private/save]
- output_mod/dipmean [real,private/save]
- output_mod/rolmean [real,private/save]
- output_mod/etotold[real,private]
- output_mod/n_v_r_file (:) [integer,private/allocatable]
- output_mod/elmean [real,private/save]
- output_mod/ntomovsets[integer,private]
- output_mod/geosmean [real,private/save]
- output_mod/timenormrms [real,private]
- output_mod/dt_cmb_file [character,private]
- output_mod/dte_file [character,private]
- output_mod/v_r_file (:) [character,private/allocatable]
- output_mod/npvsets[integer,private]
- output_mod/dlbmean [real,private/save]
- output_mod/e_kin_tmean [real,private]
- output_mod/lbdissmean [real,private/save]
- output_mod/n_t_r_sets (:) [integer,private/allocatable]
- output_mod/rmmean [real,private/save]
- output_mod/n_dt_cmb_file [integer,private]
- output_mod/n_v_r_sets (:) [integer,private/allocatable]
- output_mod/dmbmean [real,private/save]
- output_mod/n_cmb_setsmov [integer,private]
- output_mod/n_b_r_sets(:)[integer,private/allocatable]
- output_mod/n_t_r_file (:) [integer,private/allocatable]
- output_mod/ntormssets[integer,private]
- output_mod/n_e_sets[integer,private]
- output_mod/nlogs [integer,private]

- output_mod/e_kin_pmean [real,private]
- output_mod/cmb_file [character,private]
- output_mod/dteint [real,private]
- output_mod/nvpotsets[integer,private]
- output_mod/par_file [character,private]
- output mod/dmvmean [real,private/save]
- output_mod/lvdissmean [real,private/save]
- output_mod/cmbmov_file [character,private]
- output_mod/n_dt_cmb_sets[integer,private]
- output_mod/e_mag_pmean [real,private]
- output_mod/elcmbmean [real,private/save]
- output_mod/timenormlog [real,private]
- output_mod/n_cmb_file [integer,private]
- output_mod/e_mag_tmean [real,private]
- output_mod/timepassedrms [real,private]
- output_mod/dzvmean [real,private/save]
- output_mod/dlvcmean [real,private/save]
- output_mod/b_r_file (:) [character,private/allocatable]
- output_mod/n_spec [integer,private]
- output_mod/n_b_r_file (:) [integer,private/allocatable]
- output_mod/dipcmbmean [real,private/save]
- output_mod/nrms_sets[integer,private]

Subroutines and functions

subroutine output_mod/output (time, dt, dtnew, n_time_step, l_stop_time, l_bpot, l_vpot, l_tpot, l_log, l_graph, lrmscalc, l_store, l_new_rst_file, l_spectrum, ltocalc, ltoframe, ltozwrite, l_frame, n_frame, l_cmb, n_cmb_sets, l_r, lorentz_torque_ic, lorentz_torque_ma, dbdt_cmb_lmloc, hellmr, hel2lmr, helnalmr, helna2lmr, visclmr, uhlmr, duhlmr, gradslmr, fconvlmr, fkinlmr, fvisclmr, fpoynlmr, freslmr, eperplmr, eparlmr, eperpaxilmr, eparaxilmr)

This subroutine controls most of the output.

Parameters

• time [real,in]

- **dt** [real,in]
- **dtnew** [real,in]
- n_time_step [integer,in]
- l_stop_time [logical,in]
- **l_bpot** [logical,in]
- **l_vpot** [logical,in]
- **l_tpot** [logical,in]
- **l_log** [logical,in]
- l_graph [logical,in]
- **lrmscalc** [logical,in]
- **l_store** [logical,in]
- l_new_rst_file [logical,in]
- l_spectrum [logical,in]
- **ltocalc** [logical,in]
- **Itoframe** [logical,in]
- **ltozwrite** [logical,inout]
- **l_frame** [logical,in]
- **n_frame** [integer,inout]
- l_cmb [logical,in]
- n_cmb_sets [integer,inout]
- l_r [logical,in]
- lorentz_torque_ic [real,in]
- lorentz_torque_ma [real,in]
- **dbdt_cmb_lmloc** (*ulmmag-*(*llmmag*)+1) [*complex*,*in*]
- **hellmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **hel2lmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- helnalmr (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- helna2lmr (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **visclmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **uhlmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- $\mathbf{duhlmr}(l_max+1,nrstop-(nrstart)+1)[real,in]$
- $\bullet \ \ \mathbf{gradsImr} \ (l_max + 1, nrstop (nrstart) + 1) \ [real, in] \\$
- **fconvlmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **fkinlmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real,in*]
- **fvisclmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **fpoynlmr** (*l_maxmag+1,nrstopmag-(nrstartmag)+1*) [real,in]

- **freslmr** (*l_maxmag+1,nrstopmag-(nrstartmag)+1*) [real,in]
- **eperplmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **eparlmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **eperpaxilmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- eparaxilmr (l max+1,nrstop-(nrstart)+1) [real,in]

Called from step time()

```
Call to write_rot(), get_e_kin(), get_e_mag(), get_amplitude(),
    spectrum(), spectrum_temp(), fields_average(), get_power(),
    get_u_square(), outperppar(), getdlm(), outpar(), outheat(),
    outhelicity(), getegeos(), outto(), get_dtblmfinish(), zerorms(),
    dtvrms(), dtbrms(), write_bcmb(), write_coeff_r(), write_pot(),
    rbrspec(), rbpspec(), store(), gather_from_lo_to_rank0(),
    gather_all_from_lo_to_rank0(), movie_gather_frames_to_rank0(),
    store_movie_frame_ic(), logwrite(), write_movie_frame(),
    graphout_ic(), rint_r(), outomega(), outpv()
```

10.15.2 kinetic_energy.f90

Quick access

- horizontal_data (dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision_mod: This module controls the precision used in MagIC
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (cc2real ()): library with several useful subroutines
- output_data(tag()): This module contains the parameters for output control
- logic(l_non_rot(), l_save_out(), l_anel()): Module containing the logicals that control the run
- lmloop_data(llm(), ulm())
- integration (rint_r()): Radial integration functions
- parallel_mod: This module contains the blocking information
- communications(get_global_sum())
- num_param(escale(), tscale()): Module containing numerical and control parameters
- physical_parameters (nvarcond(), prmag(), ek()): Module containing the physical parameters
- truncation (1_max(), n_r_max()): This module defines the grid points and the truncation
- blocking (lo_map(), st_map()): Module containing blocking information

- constants (one (), osq4pi(), three (), two (), four (), half (), vol_oc(), pi()): module containing constants and parameters used in the code.
- radial_functions (rscheme_oc(), orho1(), orho2(), r_cmb(), or2(), or1(), r(), r_icb(), sigma()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

- kinetic_energy/e_pa(:)[real,private/allocatable]
- kinetic_energy/n_e_kin_file [integer,private]
- kinetic_energy/e_ta(:)[real,private/allocatable]
- kinetic_energy/n_u_square_file [integer,private]
- kinetic_energy/u_square_file [character,private]
- kinetic_energy/**e_p_asa** (:) [real,private/allocatable]
- kinetic_energy/e_t_asa(:) [real,private/allocatable]
- kinetic_energy/e_kin_file [character,private]

Subroutines and functions

Parameters

- **time** [real,in] :: Current time
- **l_write** [logical,in] :: Switch to write output
- **l_stop_time** [logical,in] :: Indicates when last time step of the run is reached for radial output
- n_e_sets [integer,in] :: Switch for time-average and to determine first time step
- \mathbf{w} (ulm-(llm)+1,n_r_max) [complex,in]
- **dw** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **e_p** [real,out] :: poloidal energy
- **e_t** [real,out] :: toroidal energy
- **e_p_as** [real,out] :: axisymmetric poloidal energy
- **e_t_as** [real,out] :: axisymmetric toroidal energy

Options ekinr (*n_r_max*) [real,out,optional] :: Radial profile of kinetic energy

```
Called from fields_average(), output()
Call to cc2real(), rint_r()
```

subroutine kinetic_energy/get_u_square(time, w, dw, z, rolr, dlr, dlrc)

calculates square velocity = 1/2 Integral ($v^2 dV$) integration in theta,phi by summation of spherical harmonics integration in r by using Chebychef integrals

Write the different contributions in u square. TAG file

Parameters

- **time** [real,in] :: Current time
- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- \mathbf{dw} (ulm-(llm)+1,n_r_max) [complex,in]
- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- rolr (n_r_max) [real,out] :: local Rossby number
- **dlr** (*n_r_max*) [real,out] :: Length scale
- **dlrc** (*n_r_max*) [*real,out*] :: Convective length scale

```
Called from output()
Call to cc2real(), rint_r()
```

10.15.3 magnetic energy.f90

Quick access

```
Variables lm_max_comp, n_compliance_file, n_dipole_file, n_e_mag_ic_file,
    n_e_mag_oc_file, n_phi_max_comp, n_theta_max_comp, dipole_file,
    e_mag_ic_file, e_mag_oc_file, earth_compliance_file, bcmb, e_dipa,
    e_p_asa, e_pa, e_t_asa, e_ta, plm_comp
Routines finalize_magnetic_energy(), initialize_magnetic_energy(),
    get_br_skew(), get_e_mag()
```

- horizontal_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision_mod: This module controls the precision used in MagIC
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (cc22real (), cc2real ()): library with several useful subroutines
- movie_data (moviedipstrengthgeo(), moviedipstrength(), moviedipcolat(), moviediplon())
- output_data (tag(), 1_max_comp()): This module contains the parameters for output control
- communications (gather_from_lo_to_rank0())

- logic(l_save_out(), l_earth_likeness(), l_cond_ic(), l_mag(), l_mag_lf()): Module containing the logicals that control the run
- lmloop_data(llmmag(), ulmmag())
- radial_data (n_r_cmb()): This module defines the MPI decomposition in the radial direction.
- parallel_mod: This module contains the blocking information
- integration (rint_r(), rintic()): Radial integration functions
- plms_theta(plm_theta())
- special (n_imp(), rrmp()): This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- num_param (escale (), tscale ()): Module containing numerical and control parameters
- physical_parameters (ktopb(), lffac(), kbotb()): Module containing the physical parameters
- truncation (n_r_ic_max(), n_r_ic_maxmag(), minc(), n_r_max(), lm_max(), n_r_maxmag()): This module defines the grid points and the truncation
- blocking (lo_map(), lmstartb(), st_map(), lmstopb()): Module containing blocking information
- constants (osq4pi(), two(), one(), four(), zero(), half(), pi()): module containing constants and parameters used in the code.
- radial_functions (rscheme_oc(), orhol(), r_cmb(), dr_fac_ic(), or2(), r_ic(), r(), r_icb(), chebt_ic(), sigma()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

- magnetic_energy/bcmb (:) [complex,private/allocatable]
- magnetic_energy/e_pa (:) [real,private/allocatable]
- magnetic_energy/e_ta(:) [real,private/allocatable]
- magnetic_energy/e_t_asa(:)[real,private/allocatable]
- magnetic_energy/n_phi_max_comp [integer,private]
- magnetic_energy/n_theta_max_comp [integer,private]
- magnetic_energy/e_mag_ic_file [character,private]
- magnetic_energy/earth_compliance_file [character,private]
- magnetic_energy/dipole_file [character,private]
- magnetic_energy/n_e_mag_ic_file [integer,private]
- magnetic_energy/e_mag_oc_file [character,private]
- magnetic_energy/e_dipa(:) [real,private/allocatable]
- magnetic_energy/n_compliance_file [integer,private]
- magnetic_energy/e_p_asa(:)[real,private/allocatable]
- magnetic_energy/n_dipole_file [integer,private]
- magnetic_energy/plm_comp (:,:) [real,private/allocatable]

- magnetic_energy/n_e_mag_oc_file [integer,private]
- magnetic_energy/lm_max_comp [integer,private]

Subroutines and functions

```
subroutine magnetic_energy/initialize_magnetic_energy()
   Open diagnostic files and allocate memory
        Called from magic
        Call to plm_theta()
subroutine magnetic_energy/finalize_magnetic_energy()
   Close file and deallocates global arrays
```

Called from magic

calculates magnetic energy = 1/2 Integral(B^2 dV) integration in theta,phi by summation over harmonic coeffs. integration in r by Chebyshev integrals or Simpson rule depending whether FD or Cheb is used.

- **time** [real,in] :: Current time
- **l_write** [logical,in] :: Switch to write output
- **l_stop_time** [logical,in] :: Indicates when last time step of the run is reached for radial output
- n_e_sets [integer,in] :: Switch for time-average and to determine first time step
- **b** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **db** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **aj** (*ulmmag-(llmmag)*+1,*n_r_maxmag*) [*complex*,*in*]
- **b_ic** (*ulmmag-(llmmag)+1,n_r_ic_maxmag*) [*complex,in*]
- **db_ic** (*ulmmag-(llmmag)+1,n_r_ic_maxmag*) [*complex,in*]
- aj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,in]
- e p [real,out] :: Volume averaged poloidal magnetic energy
- e_t [real,out] :: Volume averaged toroidal magnetic energy
- e_p_as [real,out] :: Volume averaged axisymmetric poloidal magnetic energy
- e_t_as [real,out] :: Volume averaged axisymmetric toroidal magnetic energy
- e_p_ic [real,out] :: IC poloidal magnetic energy
- e_t_ic [real,out] :: IC toroidal magnetic energy
- e_p_as_ic [real,out] :: IC axisymmetric poloidal magnetic energy
- e_t_as_ic [real,out] :: IC axisymmetric toroidal magnetic energy

- e_p_os [real,out] :: Outside poloidal magnetic energy
- e_p_as_os [real,out] :: Outside axisymmetric poloidal magnetic energy
- e_cmb [real,out] :: Magnetic energy at the CMB
- **dip** [real,out] :: Relative magnetic energy of axial dipole
- **dipcmb** [real,out] :: Relative magnetic energy of axial dipole at the CMB
- **elsanel** [real,out] :: Radially averaged Elsasser number

```
Called from fields_average(), output()
Call to cc2real(), gather_from_lo_to_rank0(), rint_r(), cc22real(),
    rintic(), get br skew()
```

```
subroutine magnetic_energy/get_br_skew(bcmb, br_skew)
```

This subroutine calculates the skewness of the radial magnetic field at the outer boundary. bskew := $\langle B^4 \rangle / \langle B^2 \rangle^2$ where $\langle ... \rangle$ is average over the surface

Parameters

- **bcmb** (*lm_max*) [*complex*,*in*]
- **br skew** [real,out]

Called from get_e_mag()

10.15.4 getDlm.f90

Description

This module is used to calculate the lengthscales

Quick access

Routines getdlm()

- horizontal_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision mod: This module controls the precision used in MagIC
- useful (abortrun ()): library with several useful subroutines
- lmloop_data(llm(), ulm())
- integration(rint_r()): Radial integration functions
- parallel mod: This module contains the blocking information
- num_param (escale ()): Module containing numerical and control parameters
- truncation (l_max(), minc(), n_r_max(), m_max()): This module defines the grid points and the truncation

- blocking (lo_map(), st_map()): Module containing blocking information
- constants (pi (), half ()): module containing constants and parameters used in the code.
- radial_functions (orho1 (), rscheme_oc(), r(), or2 ()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Subroutines and functions

```
subroutine getdlm_mod/getdlm(w, dw, z, dl, dlr, dm, dlc, dlrc, switch_bn)
```

calculates energy = 1/2 Integral(B² dV) integration in theta,phi by summation over harmonic coeffs. integration in r by Chebycheff integrals

Output: enbp: Total poloidal enbt: Total toroidal apome: Axisym. poloidal atome: Axisym. toroidal

Parameters

- \mathbf{w} (ulm-(llm)+1,n_r_max) [complex,in]
- \mathbf{dw} (ulm-(llm)+1,n_r_max) [complex,in]
- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **dl** [real,out]
- **dlr** (*n_r_max*) [*real,out*]
- **dm** [real,out]
- dlc [real,out]
- **dlrc** (*n_r_max*) [*real*, *out*]
- switch_bn [character,in]

```
Called from output ()
```

Call to cc2real(), abortrun(), rint_r()

10.15.5 outMisc.f90

Description

This module contains several subroutines that can compute and store various informations: helicity, heat transfer.

Quick access

Needed modules

- horizontal_data(gauss()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision_mod: This module controls the precision used in MagIC
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (cc2real ()): library with several useful subroutines
- output_data(tag()): This module contains the parameters for output control
- logic (l_hel(), l_anelastic_liquid(), l_chemical_conv(), l_heat(), l_tp_form(), l_temperature_diff(), l_save_out()): Module containing the logicals that control the run
- legendre_spec_to_grid(lmas2pt())
- integration (rint_r()): Radial integration functions
- radial_data(n_r_cmb(), nrstart(), n_r_icb(), nrstop()): This module defines the MPI decomposition in the radial direction.
- parallel_mod: This module contains the blocking information
- num_param (1scale ()): Module containing numerical and control parameters
- lmloop_data(llm(), ulm())
- physical_parameters (vischeatfac(), thexpnb()): Module containing the physical parameters
- truncation (lm_max(), l_max(), n_r_max()): This module defines the grid points and the truncation
- start_fields (botcond(), topcond(), botxicond(), deltacond(), deltaxicond(), topxicond())
- blocking (nthetabs (), nfs (), sizethetab ()): Module containing blocking information
- constants (four (), osq4pi (), two (), one (), sq4pi (), vol_oc(), pi ()): module containing constants and parameters used in the code.
- radial_functions (rscheme_oc(), kappa(), r_cmb(), rho0(), dlalpha0(), alpha0(), ogrun(), dltemp0(), beta(), temp0(), r_icb(), orho1(), r(), otemp1()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

- outmisc_mod/tmeanr(:) [real,private/allocatable]
- outmisc_mod/smeanr(:) [real,private/allocatable]
- outmisc_mod/ximeanr(:) [real,private/allocatable]
- outmisc_mod/n_heat_file [integer,private]
- outmisc_mod/pmeanr(:) [real,private/allocatable]
- outmisc_mod/helicity_file [character,private]
- outmisc_mod/heat_file [character,private]
- outmisc_mod/n_helicity_file [integer,private]

Subroutines and functions

subroutine outmisc_mod/initialize_outmisc_mod()

```
Called from magic
subroutine outmisc_mod/finalize_outmisc_mod()
          Called from magic
subroutine outmisc_mod/outhelicity(timescaled, hellmr, hel2lmr, helnalmr, helna2lmr)
          This subroutine is used to store informations about kinetic helicity
          Parameters
                • timescaled [real,in]
                • hellmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • hel2lmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • helnalmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • helna2lmr (l_max+1,nrstop-(nrstart)+1) [real,in]
          Called from output ()
          Call to Imas2pt(), rint_r()
subroutine outmisc mod/outheat (time, timepassed, timenorm, l stop time, s, ds, p, dp, xi, dxi)
          This subroutine is used to store informations about heat transfer (i.e. Nusselt number, temperature,
          entropy, ...)
          Parameters
                • time [real,in]
                • timepassed [real,in]
                • timenorm [real,in]
                • l_stop_time [logical,in]
                • s (ulm-(llm)+1,n_r_max) [complex,in]
                • ds (ulm-(llm)+1,n\_r\_max) [complex,in]
                 • p (ulm-(llm)+1,n_r_max) [complex,in]
                • dp (ulm-(llm)+1,n\_r\_max) [complex,in]
                • xi (ulm-(llm)+1,n_r_max) [complex,in]
                • dxi (ulm-(llm)+1,n_r_max) [complex,in]
          Called from output ()
          Call to rint r()
```

10.15.6 outRot.f90

Quick access

Needed modules

- horizontal_data (gauss (), costheta ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision_mod: This module controls the precision used in MagIC
- useful (abortrun ()): library with several useful subroutines
- output_data(tag()): This module contains the parameters for output control

get_viscous_torque_real(), get_angular_moment()

- logic (l_rot_ic(), l_finite_diff(), l_drift(), l_iner(), l_save_out(), l_srma(), l_mag_lf(), l_rot_ma(), l_am(), l_sric(), l_mag()): Module containing the logicals that control the run
- lmloop_data(ulmmag(), llmmag(), llm(), ulm())
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction
- parallel_mod: This module contains the blocking information
- integration (rint_r()): Radial integration functions
- special (lgrenoble(), bic()): This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- num_param(tscale(), lscale(), vscale()): Module containing numerical and control parameters
- physical parameters (kbotv(), ktopv()): Module containing the physical parameters
- truncation (nrp(), minc(), n_phi_max(), n_r_max(), n_r_maxmag()): This module defines the grid points and the truncation
- blocking (lo_map(), lmstartb(), st_map(), lm2(), lmstopb()): Module containing blocking information
- constants (c_moi_oc(), y11_norm(), third(), y10_norm(), two(), four(), zero(), c_moi_ic(), half(), c_moi_ma(), pi()): module containing constants and parameters used in the code.
- radial_functions (r_icb(), r_cmb(), rscheme_oc(), r()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

- outrot/n_inerp_file [integer,private]
- outrot/inert_file [character,private]
- outrot/rot_file [character,private]
- outrot/driftvd_file [character,private]
- outrot/srma_file [character,private]
- outrot/sric_file [character,private]
- outrot/driftvq_file [character,private]
- outrot/n_driftvq_file [integer,private]
- outrot/n_driftvd_file [integer,private]
- outrot/get_viscous_torque [public]
- outrot/driftbq_file [character,private]
- outrot/n_inert_file [integer, private]
- outrot/angular_file [character,private]
- outrot/n_angular_file [integer,private]
- outrot/driftbd_file [character,private]
- outrot/n_srma_file [integer,private]
- outrot/n_rot_file [integer,private]
- outrot/n_driftbq_file [integer,private]
- outrot/inerp_file [character,private]
- outrot/n_sric_file [integer,private]
- outrot/n_driftbd_file [integer,private]

Subroutines and functions

```
subroutine outrot/initialize_outrot()
Called from magic
```

subroutine outrot/finalize_outrot()

Called from magic

subroutine outrot/write_rot(time, dt, ekinic, ekinma, w, z, dz, b, omega_ic, omega_ma, lorentz_torque_ic, lorentz_torque_ma)

- time [real,in]
- dt [real,in]
- **ekinic** [real,out]
- ekinma [real,out]
- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]

- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **dz** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **b** (*ulmmag-(llmmag)+1,n_r_maxmag*) [*complex,in*]
- omega_ic [real,in]
- omega_ma [real,in]
- lorentz torque ic [real,in]
- lorentz_torque_ma [real,in]

Called from output ()

Call to sendvals_to_rank0(), get_angular_moment()

subroutine outrot/get_viscous_torque_real (viscous_torque, z10, dz10, r)

Purpose of this subroutine is to calculate the viscous torque on mantle or inner core respectively. NOTE: sign is wrong for torque on mantle!

Parameters

- viscous torque [real,out]
- **z10** [real,in] :: z10 coefficient and its radial deriv.
- **dz10** [real,in]
- r [real,in] :: radius (ICB or CMB)

subroutine outrot/get_viscous_torque_complex(viscous_torque, z10, dz10, r)

Purpose of this subroutine is to calculate the viscous torque on mantle or inner core respectively. NOTE: sign is wrong for torque on mantle!

Parameters

- viscous_torque [real,out]
- **z10** [complex,in] :: z10 coefficient and its radial deriv.
- dz10 [complex,in]
- **r** [real,in] :: radius (ICB or CMB)

subroutine outrot/**get_lorentz_torque**(lorentz_torque, nthetastart, sizethetab, br, bp, nr)

Purpose of this subroutine is to calculate the lorentz torque on mantle or inner core respectively. Blocking in theta can be used to increased performance. If no blocking required set n_theta_block=n_theta_max, where n_theta_max is the absolut number of thetas used.

Note: Lorentz_torque must be set to zero before loop over theta blocks is started.

Warning: subroutine returns -lorentz_torque if used at CMB to calculate torque on mantle because if the inward surface normal vector.

The Prandtl number is always the Prandtl number of the outer core. This comes in via scaling of the magnetic field. Theta alternates between northern and southern hemisphere in br and bp but not in gauss. This has to be cared for, and we use: gauss(latitude)=gauss(-latitude) here.

Parameters

- **lorentz_torque** [real,inout] :: lorentz_torque for theta(1:n_theta)
- **nthetastart** [integer,in] :: first number of theta in block
- sizethetab [integer,in] :: size of theta bloching
- **br** (*nrp*,*) [real,in] :: array containing
- **bp** (*nrp*,*) [real,in] :: array containing
- **nr** [integer,in]

Called from do_iteration_thetablocking_openmp(), do_iteration_thetablocking_seq(),
 do_iteration_thetablocking_shtns()

subroutine outrot/**get_angular_moment**(z10, z11, omega_ic, omega_ma, angular_moment_oc, angular_moment_ic, angular_moment_ma)

Calculates angular momentum of outer core, inner core and mantle. For outer core we need z(1=1)m=0,1r, for inner core and mantle the respective rotation rates are needed.

Parameters

- **z10** (*n_r_max*) [complex,in]
- **z11** (*n r max*) [complex,in]
- omega_ic [real,in]
- omega_ma [real,in]
- angular_moment_oc (*) [real,out]
- angular_moment_ic (*) [real,out]
- angular_moment_ma (*) [real,out]

Called from write_rot(), updatez()

Call to rint_r()

subroutine outrot/sendvals_to_rank0 (field, n_r, lm_vals, vals_on_rank0)

Parameters

- **field** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **n_r** [integer,in]
- lm_vals (*) [integer,in]
- vals_on_rank0 (*) [complex,out]

Called from write_rot()

Call to abortrun()

10.15.7 outPar.f90

Description

This module is used to compute several time-averaged radial profiles: fluxes, boundary layers, etc.

Quick access

```
Variables n_perppar_file, perppar_file, dlvcmeanr, dlvmeanr, dlvu2cmeanr, dlvu2meanr, duhmeanr, eparaximeanr, eparameanr, eperpaximeanr, eperpmeanr, fcondmeanr, fconvmeanr, fkinmeanr, fpoynmeanr, fresmeanr, fviscmeanr, gradt2meanr, mvar, rmmeanr, rolmeanr, rolmeanru2, smeanr, svar, uhmeanr
```

```
Routines finalize_outpar_mod(), initialize_outpar_mod(), outperppar(), outpar()
```

- horizontal_data(gauss()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision_mod: This module controls the precision used in MagIC
- output data (tag()): This module contains the parameters for output control
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (cc2real ()): library with several useful subroutines
- fields (ds_rloc(), dp_rloc(), s_rloc(), p_rloc()): This module contains the potential fields and their radial derivatives
- num_param(tscale()): Module containing numerical and control parameters
- legendre_spec_to_grid(lmas2pt())
- integration (rint_r()): Radial integration functions
- radial_data(nrstartmag(), nrstart(), nrstopmag(), n_r_icb(), nrstop()): This module defines the MPI decomposition in the radial direction.
- parallel mod: This module contains the blocking information
- logic (l_anelastic_liquid(), l_mag_nl(), l_tp_form(), l_temperature_diff(), l_save_out(), l_anel(), l_perppar(), l_fluxprofs(), l_viscbccalc()): Module containing the logicals that control the run
- physical_parameters (prmag(), kbots(), ek(), opr(), ekscaled(), vischeatfac(), ktops(), thexpnb(), ohmlossfac()): Module containing the physical parameters
- radial_functions (rscheme_oc(), kappa(), dlalpha0(), rho0(), or2(), alpha0(), dltemp0(), beta(), temp0(), orho1(), r(), sigma()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (lm2m(), nthetabs(), nfs(), sizethetab()): Module containing blocking information

- constants (four (), osq4pi (), two (), sq4pi (), mass (), half (), pi ()): module containing constants and parameters used in the code.
- truncation (lm_max(), l_max(), l_maxmag(), n_r_max(), n_r_maxmag()): This module defines the grid points and the truncation

- outpar_mod/fconvmeanr (:) [real,private/allocatable]
- outpar_mod/eparmeanr (:) [real,private/allocatable]
- outpar_mod/dlvcmeanr (:) [real,private/allocatable]
- outpar_mod/dlvu2cmeanr(:) [real,private/allocatable]
- outpar_mod/fcondmeanr(:) [real,private/allocatable]
- outpar_mod/rolmeanru2 (:) [real,private/allocatable]
- outpar_mod/eparaximeanr (:) [real,private/allocatable]
- outpar_mod/fpoynmeanr (:) [real,private/allocatable]
- outpar_mod/rolmeanr(:) [real,private/allocatable]
- outpar_mod/fresmeanr (:) [real,private/allocatable]
- outpar_mod/fviscmeanr(:) [real,private/allocatable]
- outpar_mod/duhmeanr(:) [real,private/allocatable]
- outpar_mod/rmmeanr(:) [real,private/allocatable]
- outpar_mod/mvar (:) [real,private/allocatable]
- outpar_mod/smeanr (:) [real,private/allocatable]
- outpar_mod/gradt2meanr(:) [real,private/allocatable]
- outpar_mod/dlvu2meanr(:) [real,private/allocatable]
- outpar_mod/fkinmeanr (:) [real,private/allocatable]
- outpar_mod/n_perppar_file [integer,private]
- outpar_mod/uhmeanr(:) [real,private/allocatable]
- outpar_mod/svar(:) [real,private/allocatable]
- outpar mod/eperpaximeanr(:) [real,private/allocatable]
- outpar_mod/**dlvmeanr**(:) [real,private/allocatable]
- outpar_mod/perppar_file [character,private]
- outpar_mod/eperpmeanr (:) [real,private/allocatable]

Subroutines and functions

Called from magic

subroutine outpar_mod/**outpar** (timepassed, timenorm, nlogs, l_stop_time, ekinr, rolru2, dlvr, dlvrc, dlvru2, dlvru2c, uhlmr, duhlmr, gradslmr, fconvlmr, fkinlmr, fvisclmr, fpoynlmr, freslmr, rmr)

Parameters

- timepassed [real,in]
- timenorm [real,in]
- **nlogs** [integer,in]
- l_stop_time [logical,in]
- **ekinr** (*n_r_max*) [*real,in*] :: kinetic energy w radius
- **rolru2** (*n_r_max*) [*real,in*]
- **dlvr** (*n_r_max*) [*real,in*]
- **dlvrc** (*n_r_max*) [*real,in*]
- **dlvru2** (*n_r_max*) [*real,in*]
- **dlvru2c** (*n_r_max*) [*real,in*]
- **uhlmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **duhlmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- gradslmr (l_max+1,nrstop-(nrstart)+1) [real,in]
- **fconvlmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **fkinlmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real,in*]
- **fvisclmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **fpoynlmr** (*l_maxmag+1,nrstopmag-(nrstartmag)+1*) [real,in]
- **freslmr** (*l_maxmag+1,nrstopmag-(nrstartmag)+1*) [real,in]
- **rmr** (*n*_*r*_*max*) [real,out]

Called from output ()

Call to cc2real(), 1mas2pt()

- time [real,in]
- timepassed [real,in]
- **timenorm** [real,in]
- l_stop_time [logical,in]
- **eperplmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **eparlmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **eperpaxilmr** (*l_max*+1,*nrstop*-(*nrstart*)+1) [*real,in*]
- eparaxilmr (l_max+1,nrstop-(nrstart)+1) [real,in]

```
Called from output()
Call to lmas2pt(), rint r()
```

10.15.8 power.f90

Quick access

```
Variables n_calls, n_power_file, power_file, ediffint, powerdiff, buo_chemr_mean, buo_chemr_sd, buor_mean, buor_sd, ohmdissr_mean, ohmdissr_sd, vischeatr_mean, vischeatr_sd
```

Routines finalize_output_power(), initialize_output_power(), get_power()

- horizontal_data(dlh(), gauss()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision_mod: This module controls the precision used in MagIC
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- outrot(get_viscous_torque())
- useful (round_off(), get_mean_sd(), cc22real(), cc2real()): library with several useful subroutines
- output_data(tag()): This module contains the parameters for output control
- logic (l_rot_ic(), l_anelastic_liquid(), l_chemical_conv(), l_mag(), l_save_out(), l_srma(), l_rot_ma(), l_heat(), l_tp_form(), l_sric(), l_cond_ic(), l_conv()): Module containing the logicals that control the run
- legendre_spec_to_grid(lmas2pt())
- lmloop_data(ulmmag(), llmmag(), llm(), ulm())
- radial_data(n_r_cmb(), nrstart(), n_r_icb(), nrstop()): This module defines the MPI decomposition in the radial direction.
- parallel_mod: This module contains the blocking information
- integration(rint_r(), rintic()): Radial integration functions
- num_param (escale (), tscale ()): Module containing numerical and control parameters
- physical_parameters (kbotv(), buofac(), lffac(), vischeatfac(), ktopv(), chemfac(), opm(), thexpnb()): Module containing the physical parameters
- truncation (n_r_ic_max(), l_max(), n_r_maxmag(), n_r_ic_maxmag(), n_r_max()): This module defines the grid points and the truncation
- blocking (lmstartb(), nthetabs(), sizethetab(), nfs(), lmstopb(), lo_map(), st map()): Module containing blocking information
- constants (half (), two (), one ()): module containing constants and parameters used in the code.

• radial_functions (rscheme_oc(), orhol(), r_ic(), r_cmb(), o_r_ic2(), or2(), alpha0(), rgrav(), r(), temp0(), o_r_ic(), dr_fac_ic(), r_icb(), chebt_ic(), otemp1(), lambda()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

- power/buo_chemr_sd(:) [real,private/allocatable]
- power/powerdiff [real,private]
- power_file [character, private]
- power/buor_mean (:) [real,private/allocatable]
- power/ohmdissr_sd(:) [real,private/allocatable]
- power/n_power_file [integer,private]
- power/ohmdissr_mean (:) [real,private/allocatable]
- power/vischeatr_sd(:) [real,private/allocatable]
- power/n_calls[integer,private]
- power/vischeatr_mean (:) [real,private/allocatable]
- power/ediffint [real,private]
- power/buor_sd(:) [real,private/allocatable]
- power/buo_chemr_mean (:) [real,private/allocatable]

Subroutines and functions

subroutine power/**get_power** (time, timepassed, timenorm, l_stop_time, omega_ic, omega_ma, lorentz_torque_ic, lorentz_torque_ma, w, z, dz, s, p, xi, b, ddb, aj, dj, db ic, ddb ic, aj ic, dj ic, visclmr, viscdiss, ohmdiss)

This subroutine calculates power and dissipation of the core/mantle system. Energy input into the outer core is by buoyancy and possibly viscous accelarations at the boundaries if the rotation rates of inner core or mantle are prescribed and kept fixed. The losses are due to Ohmic and viscous dissipation. If inner core and mantel are allowed to change their rotation rates due to viscous forces this power is not lost from the system and has to be respected.

The output is written into a file power.TAG.

- time [real,in]
- timepassed [real,in]
- timenorm [real,in]

```
• l_stop_time [logical,in]
```

- omega_ic [real,in]
- omega_ma [real,in]
- lorentz_torque_ic [real,in]
- lorentz_torque_ma [real,in]
- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- dz (ulm-(llm)+1, n_r_max) [complex,in]
- \mathbf{s} (ulm-(llm)+1,n_r_max) [complex,in]
- **p** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **xi** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **b** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **ddb** (*ulmmag*-(*llmmag*)+1,*n_r_maxmag*) [*complex*,*in*]
- **aj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **dj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **db_ic** (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,in]
- **ddb_ic** (*ulmmag-(llmmag*)+1,*n_r_ic_maxmag*) [*complex,in*]
- aj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,in]
- **dj_ic** (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,in]
- visclmr (l max+1,nrstop-(nrstart)+1) [real,in]
- viscdiss [real,out]
- **ohmdiss** [real,out]

Called from output ()

Call to Imas2pt(), cc2real(), cc22real(), rint_r(), rintic(), round_off()

10.15.9 spectra.f90

Quick access

Variables n_am_kpol_file, n_am_ktor_file, n_am_mpol_file, n_am_mtor_file, n_kin_spec_file, n_mag_spec_file, n_temp_spec_file, n_u2_spec_file, am_kpol_file, am_ktor_file, am_mpol_file, am_mtor_file, dt_icb_l_ave, dt_icb_l_sd, dt_icb_m_ave, dt_icb_m_sd, e_kin_p_l_ave, e_kin_p_l_sd, e_kin_p_m_ave, e_kin_p_m_sd, e_kin_t_l_ave, e_kin_t_l_sd, e_kin_t_m_ave, e_kin_t_m_sd, e_mag_cmb_l_ave, e_mag_cmb_l_sd, e_mag_cmb_m_ave, e_mag_cmb_m_sd, e_mag_p_l_ave, e_mag_p_l_sd, e_mag_p_m_ave, e_mag_t_l_sd, e_mag_t_l_ave, e_mag_t_l_sd, e_mag_t_m_ave, e_mag_t_m_sd, t_icb_l_ave, t_icb_l_sd, t_icb_m_ave, t_icb_m_sd, t_l_ave, t_l_sd, t_m_ave, t_m_sd, u2_p_l_ave, u2_p_l_sd, u2_p_m_ave, u2_p_m_sd, u2_t_l_sd, u2_t_m_ave, u2_t_m_sd,

```
e_kin_p_r_l_ave, e_kin_p_r_m_ave, e_kin_t_r_l_ave, e_kin_t_r_m_ave,
e_mag_p_r_l_ave, e_mag_p_r_m_ave, e_mag_t_r_l_ave, e_mag_t_r_m_ave
Routines finalize_spectra(), initialize_spectra(), spectrum_temp(),
spectrum(), get_amplitude()
```

Needed modules

- horizontal_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision_mod: This module controls the precision used in MagIC
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (abortrun(), get_mean_sd(), cc22real(), cc2real()): library with several useful subroutines
- output_data (n_log_file(), tag(), m_max_modes(), log_file()): This module contains the parameters for output control
- logic (l_mag(), l_heat(), l_anel(), l_2d_spectra(), l_save_out(), l_energy_modes(), l_cond_ic()): Module containing the logicals that control the run
- lmloop_data(ulmmag(), llmmag(), llm(), ulm())
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- parallel_mod: This module contains the blocking information
- integration (rint_r(), rintic()): Radial integration functions
- num_param (escale(), tscale()): Module containing numerical and control parameters
- physical_parameters (lffac()): Module containing the physical parameters
- truncation (n_r_ic_max(), l_max(), n_r_ic_maxmag(), minc(), n_r_max(), n_r_maxmag()): This module defines the grid points and the truncation
- blocking (lo_map(), st_map()): Module containing blocking information
- constants (one (), four (), vol_oc(), pi(), half()): module containing constants and parameters used in the code.
- radial_functions (rscheme_oc(), orho1(), orho2(), dr_fac_ic(), or2(), r_ic(), r(), r_icb(), chebt_ic()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

- spectra/e_mag_t_l_ave (:) [real,private/allocatable]
- spectra/dt_icb_l_ave (:) [real,private/allocatable]
- spectra/t_m_sd(:) [real,private/allocatable]
- spectra/e_mag_p_l_ave(:) [real,private/allocatable]
- spectra/n_kin_spec_file [integer,private]

- spectra/u2_t_1_sd(:) [real,private/allocatable]
- spectra/n_u2_spec_file [integer,private]
- spectra/am_mtor_file [character,private]
- spectra/e_kin_p_m_ave (:) [real,private/allocatable]
- spectra/e_mag_cmb_l_ave (:) [real,private/allocatable]
- spectra/e_mag_cmb_l_sd(:) [real,private/allocatable]
- spectra/**e_kin_p_m_sd**(:) [real,private/allocatable]
- spectra/e_kin_t_l_sd(:) [real,private/allocatable]
- spectra/e_mag_p_m_ave(:) [real,private/allocatable]
- spectra/e_kin_t_m_ave(:) [real,private/allocatable]
- spectra/e_mag_t_m_sd(:) [real,private/allocatable]
- spectra/e_kin_t_r_l_ave (:,:) [real,private/allocatable]
- spectra/t_l_sd(:) [real,private/allocatable]
- spectra/t_l_ave(:) [real,private/allocatable]
- spectra/u2_p_m_ave(:) [real,private/allocatable]
- spectra/e_mag_p_m_sd(:) [real,private/allocatable]
- spectra/dt_icb_m_ave(:) [real,private/allocatable]
- spectra/n_am_kpol_file [integer,private]
- spectra/am_kpol_file [character,private]
- spectra/dt_icb_l_sd(:) [real,private/allocatable]
- spectra/e_kin_p_r_l_ave (:,:) [real,private/allocatable]
- spectra/am_mpol_file [character,private]
- spectra/e_mag_t_r_l_ave (:,:) [real,private/allocatable]
- spectra/e_mag_t_m_ave(:) [real,private/allocatable]
- spectra/e_mag_t_r_m_ave (:,:) [real,private/allocatable]
- spectra/**e_kin_t_r_m_ave** (:,:) [real,private/allocatable]
- spectra/n_am_mtor_file [integer,private]
- spectra/u2_t_1_ave (:) [real,private/allocatable]
- spectra/e_mag_p_r_l_ave (:,:) [real,private/allocatable]
- spectra/e_mag_p_l_sd(:) [real,private/allocatable]
- spectra/u2_p_1_sd(:) [real,private/allocatable]
- spectra/e_kin_t_m_sd(:) [real,private/allocatable]
- spectra/u2_t_m_ave(:) [real,private/allocatable]
- spectra/u2_p_m_sd(:) [real,private/allocatable]
- spectra/t_icb_1_sd(:) [real,private/allocatable]
- spectra/e_mag_t_l_sd(:) [real,private/allocatable]

- spectra/t_icb_l_ave(:) [real,private/allocatable]
- spectra/t_icb_m_sd(:) [real,private/allocatable]
- spectra/u2_p_1_ave(:) [real,private/allocatable]
- spectra/t_icb_m_ave(:) [real,private/allocatable]
- spectra/e_kin_p_l_sd(:) [real,private/allocatable]
- spectra/e_mag_cmb_m_sd(:) [real,private/allocatable]
- spectra/u2_t_m_sd(:) [real,private/allocatable]
- spectra/e_mag_p_r_m_ave(:,:) [real,private/allocatable]
- spectra/e_kin_p_r_m_ave (:,:) [real,private/allocatable]
- spectra/am_ktor_file [character,private]
- spectra/dt_icb_m_sd(:) [real,private/allocatable]
- spectra/n_am_mpol_file [integer,private]
- spectra/n_temp_spec_file [integer,private]
- spectra/e_kin_p_l_ave(:) [real,private/allocatable]
- spectra/e_mag_cmb_m_ave (:) [real,private/allocatable]
- spectra/t_m_ave(:) [real,private/allocatable]
- spectra/n_mag_spec_file [integer,private]
- spectra/e_kin_t_l_ave(:) [real,private/allocatable]
- spectra/n_am_ktor_file [integer,private]

Subroutines and functions

```
subroutine spectra/initialize_spectra()
```

Called from magic

subroutine spectra/finalize_spectra()

Called from magic

subroutine spectra/**spectrum**(*n_spec*, *time*, *l_avg*, *n_time_ave*, *l_stop_time*, *time_passed*, *time_norm*, *w*, *dw*, *z*, *b*, *db*, *aj*, *b_ic*, *db_ic*, *aj_ic*)

calculates magnetic energy = 1/2 Integral(B² dV) integration in theta,phi by summation over harmonic coeffs. integration in r by Chebycheff integrals

Output: enbp: Total poloidal enbt: Total toroidal apome: Axisym. poloidal atome: Axisym. toroidal

- **n_spec** [integer,in] :: number of spectrum/call, file
- time [real,in]
- l_avg [logical,in]
- n_time_ave [integer,in]
- l_stop_time [logical,in]

```
• time_passed [real,in]
```

- time_norm [real,in]
- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **dw** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **b** (*ulmmag*-(*llmmag*)+1,*n_r_maxmag*) [*complex*,*in*]
- **db** (*ulmmag-(llmmag)+1,n_r_maxmag*) [*complex,in*]
- **aj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **b_ic** (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,in]
- **db_ic** (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,in]
- aj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,in]

Called from fields_average(), output()

Call to cc2real(), rint_r(), cc22real(), rintic()

Parameters

- **n_spec** [integer,in]
- time [real,in]
- l_avg [logical,in]
- n_time_ave [integer,in]
- l_stop_time [logical,in]
- time_passed [real,in]
- time_norm [real,in]
- **s** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **ds** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]

Called from fields_average(), output()

Call to cc2real(), rint_r()

subroutine spectra/get_amplitude(time, w, dw, z, b, db, aj)

- time [real,in]
- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **dw** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **b** (*ulmmag-(llmmag)+1,n_r_maxmag*) [*complex,in*]
- **db** (*ulmmag-(llmmag*)+1,*n_r_maxmag*) [*complex*,*in*]
- **aj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]

```
Called from output()
Call to cc2real(), rint r()
```

10.16 IO: graphic files, movie files, coeff files and potential files

10.16.1 out_graph_file.f90

Description

This module contains the subroutines that store the 3-D graphic files.

Quick access

```
Routines graphout_ic(), graph_write_mpi(), graph_write(), graphout_header(), graphout mpi header(), graphout mpi(), graphout()
```

- horizontal_data (dplm(), plm(), dlh(), theta_ord(), o_sin_theta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision_mod: This module controls the precision used in MagIC
- fft: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- output_data(n_graph_file(), runid(), graph_mpi_fh()): This module contains the parameters for output control
- logic(l_pressgraph(), l_chemical_conv(), l_cond_ic(), l_mag()): Module containing the logicals that control the run
- legendre_spec_to_grid(legtf())
- radial data (n r icb()): This module defines the MPI decomposition in the radial direction.
- parallel mod: This module contains the blocking information
- num_param (vscale()): Module containing numerical and control parameters
- physical_parameters (pr(), prmag(), ek(), sigma_ratio(), radratio(), ra()): Module containing the physical parameters
- truncation (n_r_ic_max(), lm_maxmag(), nrp(), n_r_ic_maxmag(), minc(), n_phi_max(), l_max(), l_axi(), n_r_max(), lm_max(), n_theta_max(), n_r_maxmag(), n_phi_tot()): This module defines the grid points and the truncation
- leg_helper_mod(legprep_ic())
- blocking (nthetabs (), nfs (), sizethetab ()): Module containing blocking information
- radial_functions (orho1(), r_cmb(), o_r_ic2(), or2(), or1(), r_ic(), r(), o_r_ic(), r_icb()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Subroutines and functions

subroutine graphout_mod/**graphout** (*time*, *n_r*, *vr*, *vt*, *vp*, *br*, *bt*, *bp*, *sr*, *prer*, *xir*, *n_theta_start*, *n_theta_block_size*, *lgraphheader*)

Output of components of velocity, magnetic field vector and entropy for graphics.

- n_r : (input) for $n_r = 0$ a header is written. for $n_r > 0$ values at radial level n_r are written
- vr...sr: (input) arrays with grid-point values
- n_theta_start : (input) values are written for theta-points : n_theta_start <= n_theta <= n_theta_start-1+n_theta_block

Parameters

- time [real,in]
- **n_r** [integer,in] :: radial grod point no.
- **vr** (*nrp*,*) [real,in]
- **vt** (*nrp*,*) [real,in]
- **vp** (*nrp*,*) [real,in]
- **br** (*nrp*,*) [*real*,*in*]
- **bt** (*nrp*,*) [real,in]
- **bp** (*nrp*,*) [real,in]
- **sr** (*nrp*,*) [*real*,*in*]
- **prer** (*nrp*,*) [real,in]
- **xir** (*nrp*,*) [*real*,*in*]
- n_theta_start [integer,in] :: start theta no.
- n_theta_block_size [integer,in] :: size of theta block
- **lgraphheader** [logical,inout]

```
Called from fields_average()
```

Call to graph_write()

subroutine graphout_mod/graphout_header(time)

Parameters time [real,in]

MPI version of the graphOut subroutine (use of MPI_IO)

- time [real,in]
- **n_r** [integer,in] :: radial grod point no.
- **vr** (*nrp*,*) [real,in]

```
• vt (nrp,*) [real,in]
                • vp (nrp,*) [real,in]
                • br (nrp,*) [real,in]
                • bt (nrp,*) [real,in]
                • bp (nrp,*) [real,in]
                • sr (nrp,*) [real,in]
                • prer (nrp,*) [real,in]
                • xir (nrp,*) [real,in]
                • n_theta_start [integer,in] :: start theta no.
                • n_theta_block_size [integer,in] :: size of theta block
                • lgraphheader [logical,inout]
          Called from do_iteration_thetablocking_openmp(), do_iteration_thetablocking_seq(),
              do iteration thetablocking shtns()
          Call to graph write mpi()
subroutine graphout_mod/graphout_mpi_header (time, n_r, n_theta_start, n_theta_block_size)
          Writes the header (MPI version)
```

Parameters

- time [real,in]
- **n_r** [integer,in] :: radial grod point no.
- n_theta_start [integer,in] :: start theta no.
- n_theta_block_size [integer,in] :: size of theta block

Called from radialloopg()

```
subroutine graphout_mod/graphout_ic(b_ic, db_ic, ddb_ic, aj_ic, dj_ic, bicb)
```

Purpose of this subroutine is to write inner core magnetic field onto graphic output file. If the inner core is insulating (l_cond_ic=false) the potential field is calculated from the outer core field at r=r_cmb. This version assumes that the fields are fully local on the rank which is calling this routine (usually rank 0).

- **b_ic** (lm_maxmag,n_r_ic_maxmag) [complex,in]
- **db_ic** (lm_maxmag,n_r_ic_maxmag) [complex,in]
- ddb_ic (lm_maxmag,n_r_ic_maxmag) [complex,in]
- aj_ic (lm_maxmag,n_r_ic_maxmag) [complex,in]
- **dj_ic** (lm_maxmag,n_r_ic_maxmag) [complex,in]
- **bicb** (*lm_maxmag*) [*complex*,*in*]

```
Called from fields_average(), output()
Call to legprep_ic(), legtf(), fft_thetab(), graph_write_mpi()
```

subroutine graphout_mod/**graph_write** (*n_phis*, *n_thetas*, *dummy*, *n_graph_file*)

This subroutine writes the data for one theta-band (stored in 'dummy'). Version May, 5, 2000.

Parameters

- **n_phis** [integer, in] :: number of logitudes to be printed
- **n_thetas** [integer,in] :: number of first colatitude value
- **dummy** (n_phi_max,*) [real,in] :: data
- n_graph_file [integer,in] :: output unit

Called from graphout ()

subroutine graphout_mod/**graph_write_mpi** (n_phis, n_thetas, dummy, graph_mpi_fh)

Parameters

- **n_phis** [integer,in] :: number of logitudes to be printed
- **n_thetas** [integer,in] :: number of first colatitude value
- **dummy** (n_phi_max,*) [real,in] :: data
- graph_mpi_fh [integer,in] :: mpi handle of the mpi file

Called from graphout_ic(), graphout_mpi()

10.16.2 movie.f90

Quick access

Variables n_frame_work, n_md, n_movies, n_movies_max, n_movie_fields_max, licfield, lstoremov, n_movie_const, n_movie_fields, n_movie_fields_ic, n_movie_file, n_movie_surface, n_movie_type, n_movie_field_start, n_movie_field_stop, n_movie_field_type, moviedipcolat, moviediplon, moviedipstrength, moviedipstrengthgeo, frames, movie_file, movie, t_movies, movie_const

Routines get_movie_type(), finalize_movie_data(), initialize_movie_data(), movie_gather_frames_to_rank0()

- horizontal_data(theta(), phi()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision_mod: This module controls the precision used in MagIC
- useful (abortrun(), logwrite()): library with several useful subroutines
- output_data (n_log_file(), log_file(), tag()): This module contains the parameters for output control
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- radial_data(n_r_cmb(), nrstart(), n_r_icb(), nrstop()): This module defines the MPI decomposition in the radial direction.

- parallel_mod: This module contains the blocking information
- logic (l_movie_oc(), l_dtbmovie(), l_movie_ic(), l_store_frame(), l_save_out(), l_htmovie(), l_movie()): Module containing the logicals that control the run
- charmanip (length_to_blank(), delete_string(), capitalize(), str2dble()): This module contains several useful routines to manipule character strings
- truncation (n_r_ic_max(), lmoviemem(), ldtbmem(), minc(), n_phi_max(), n_r_tot(), n_r_max(), n_theta_max()): This module defines the grid points and the truncation
- constants (pi(), one()): module containing constants and parameters used in the code.
- radial_functions (r_cmb(), r_icb(), r(), r_ic()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

- movie_data/n_frame_work [integer,public]
- movie_data/n_movies [integer, public]
- movie_data/n_movie_field_stop (6,30) [integer,public]
- movie_data/n_movie_surface (30) [integer,public]
- movie_data/n_movie_field_start (6,30) [integer, public]
- movie_data/movie_const (30) [real,public]
- movie_data/n_movies_max [integer,parameter=30/public]
 Max no. of different movies
- movie_data/n_movie_fields_max [integer,parameter=6/public]
 Max no. of fields per movie
- movie_data/n_md[integer,public]
- movie_data/frames(:) [real, allocatable/public]
- movie_data/moviediplon [real, public]
- movie_data/n_movie_fields_ic (30) [integer, public]
- movie_data/moviedipstrengthgeo [real,public]
- movie_data/n_movie_field_type (6,30) [integer,public]
- movie data/licfield(30)[logical,public]
- movie_data/movie (30) [character,public]
 Only for input
- movie_data/n_movie_file (30) [integer, public]
- movie_data/n_movie_fields (30) [integer, public]
- movie_data/t_movies (10000) [real, public]
- movie_data/n_movie_const (30) [integer, public]
- movie_data/moviedipcolat [real,public]
- movie_data/movie_file (30) [character,public]
- movie_data/lstoremov(30)[logical,public]

- movie_data/moviedipstrength [real, public]
- movie_data/n_movie_type (30) [integer,public]

Subroutines and functions

```
subroutine movie_data/initialize_movie_data()
```

This routine is called during the initialization of the code. It allows to:

- Estimate the required memory imprint and allocate the arrays accordingly
- Open the requested movie files

```
Called from magic
Call to get_movie_type()
```

subroutine movie_data/finalize_movie_data()

Close movie files

Called from magic

```
subroutine movie_data/get_movie_type()
```

Purpose of this subroutine is to identify the different movie types from the input string movies(*). Note that generally blanks are not interpreted and that the interpretation is not case sensitive. In general two informations are needed:

- 1. A word FIELDINFO that identifies the field to be plotted (e.g. Br for radial magnetic field, see list below) Possible keywords are (optional text in brackets):
 - B r[adial]: radial magnetic field
 - B t[heta]: theta component
 - B p[hi]: azimuthal component
 - B h[orizontal]: the two horizontal components
 - B a[ll]: all three components
 - FIELDLINE[S]: field lines of axisymmetric or FL poloidal field for phi=constant
 - AX[ISYMMETRIC] B or AB: axisymmetric phi component of the magnetic field for phi=constant
 - V r[adial]: radial velocity field
 - V t[heta]: theta component
 - V p[hi]: azimuthal component
 - V h[orizontal]: the two horizontal components
 - V a[ll] : all three components
 - STREAMLINE[S]: field lines of axisymmetric or SL: poloidal field for phi=constant
 - AX[ISYMMETRIC] V or AV: axisymmetric phi component of the velocity field for phi=constant
 - V z : z component of velocity at equator and z component of the vorticity at the equator (closest point to equator)
 - Vo z : z-component of vorticity
 - Vo r : r-component of vorticity

- Vo p : phi-component of vorticity
- T[emperature] : sic
- AX[ISYMMETRIC] T or AT: axisymmetric T field for phi=constant
- Heat t[ransport]: radial derivative of T
- FL Pro: axisymmetric field line stretching
- FL Adv: axisymmetric field line advection
- FL Dif: axisymmetric field line diffusion
- AB Pro: axisymmetric (tor.) Bphi production
- AB Dif: axisymmetric (tor.) Bphi diffusion
- Br Pro: Br production
- Br Adv : Br advection
- Br Dif: Br diffusion
- Jr : Jr production
- Jr Pro : Jr production + omega effects
- Jr Adv : Jr advection
- Jr Dif: Jr diffusion
- Bz Pol : poloidal Bz
- Bz Pol Pro: poloidal Bz production
- Bz Pol Adv: poloidal Bz advection
- Bz Pol Dif: poloidal Bz diffusion
- Jz Tor: poloidal Jz
- Jz Tor Pro: poloidal Jz production
- Jz Tor Adv : poloidal Jz advection
- Jz Tor Dif : poloidal Jz diffusion
- Bp Tor: toriodal Bphi
- Bp Tor Pro: toriodal Bphi production
- Bp Tor Adv: toriodal Bphi advection
- Bp Tor Dif: toriodal Bphi diffusion
- HEL[ICITY] : sic
- AX[ISYMMETRIC HELICITY] or AHEL: axisymmetric helicity
- Bt Tor: toroidal Btheta
- Pot Tor: toroidal Potential
- Pol Fieldlines: toroidal Potential
- Br Shear: azimuthal Shear of Br
- Lorentz[force] : Lorentz force (only phi component)
- Br Inv: Inverse field apperance at CMB

- 2. A second information that identifies the coordinate to be kept constant (surface). E.g. r=number for surface r=constant with number given in units of the total core radius or theta/phi=number with number given in degrees Four keywords are also possible:
 - CMB : core mantle boundary
 - EQ[UATOR] : equatorial plane
 - SUR[FACE] : Earth surface (only magnetic field)
 - 3[D]: 3D field throughout the OC [and IC for B]

On output the necessary information is coded into integers and is used in this form by further subroutines:

- n_movies = total number of movies
- n_type(n_movie) = movie type:
 - = 1 : Radial magnetic field
 - = 2: Theta component of magnetic field
 - = 3: Azimuthal magnetic field
 - = 4 : Horizontal magnetic field
 - = 5 : Total magnetic field (all compnents)
 - = 8 : Axisymmetric azimuthal magnetic field (phi=constant)
 - = 9: 3d magnetic field
 - = 11 : Radial velocity field
 - = 12: Theta component of velocity field
 - = 13 : Azimuthal velocity field
 - = 14 : Horizontal velocity field
 - = 15 : Total velocity field (all compnents)
 - = 17 : Scalar field whose contours are the stream lines of the axisymm. poloidal velocity field (phi=constant)
 - = 18 : Axisymmetric azimuthal velocity field (phi=constant)
 - = 19: 3d velocity field
 - = 20: z component of vorticity
 - = 21: Temperature field
 - = 22: radial conv. heat transport
 - = 23: helicity
 - = 24: axisymmetric helicity
 - = 25: phi component of vorticity
 - = 26: radial component of vorticity
 - = 28 : axisymmetric Temperature field for phi=const.
 - = 29: 3d temperature field
 - = 30 : Scalar field whose contours are the fieldlines of the axisymm. poloidal magnetic field (phi=constant)

- = 31: field line production
- = 32: field line advection
- = 33: field line diffusion
- = 40 : Axisymmetric azimuthal magnetic field (phi=constant)
- = 41 : Axis. Bphi production + omega eff.
- = 42: Axis. Bphi advection
- = 43: Axis. Bphi diffusion
- = 44 : Axis. Bphi str.,dyn.,omega,diff.
- = 50 : Bz
- = 51: Bz production
- = 52: Bz advection
- = 53: Bz diffusion
- = 60: toroidal Bphi
- = 61 : toroidal Bphi production + omega eff.
- = 62 : toroidal Bphi advection
- = 63: toroidal Bphi diffusion
- = 71: Br production
- = 72: Br advection
- = 73: Br diffusion
- = 80 : Jr
- = 81: Jr production
- = 82: Jr advection
- = 83: Jr diffusion
- = 90: poloidal Jz pol.
- = 91: poloidal Jz pol. production
- = 92: poloidal Jz advection
- = 93 : poloidal Jz diffusion
- = 94 : z component of velovity
- = 95: toroidal Btheta
- = 96 : toroidal Potential
- = 97 : Function for Poloidal Fieldlines
- = 98 : azimuthal shear of Br
- = 99 : phi component of Lorentz force
- =101 : Stress fields
- = 102: Force fields
- =103: Br Inverse appearence at CMB

- = 110: radial heat flow
- =111: Vz and Vorz north/south correlation
- =112: axisymm dtB tersm for Br and Bp
- =113: axisymm dSdr
- =114: Cylindrically radial magnetic field
- n_movie_surface(n_movie) = defines surface
- n_movie_surface = 1 : r=constant:
 - 2: theta=constant
 - 3: phi=constant
 - -1: r=constant, Earth surface
 - 0:3d volume
- n_movie_fields(n_movie) = no. of fields for outer core
- n_movie_fields_ic(n_movie) = no. of fields for inner core
- n_movie_field_type(n_field,n_movie) = defines field
- n_movie_field_type:
 - = 1 : radial magnetic field
 - = 2: theta comp. of the magnetic field
 - = 3: azimuthal magnetic field
 - = 4 : radial velocity field
 - = 5: theta comp. of the velocity field
 - = 6: azimuthal velocity field
 - = 7: temperature field
 - = 8 : scalar field for field lines
 - = 9: axisymm. toroidal mag. field
 - =10: scalar field for stream lines
 - =11 : axisymm. v_phi
 - =12: axisymm. T
 - =13 : z-comp. of poloidal Bz
 - =14 : z-comp. of poloidal Jz
 - = 15: z-comp. of velocity
 - =16: z-comp. of vorticity
 - = 17: radial derivative of T * vr
 - = 18: helicity
 - =19: axisymmetric helicity
 - =20: axisymm field-line production
 - =21 : axisymm field-line advection

- =22 : axisymm field-line diffusion
- =23: axisymm Bphi production
- =24 : axisymm Bphi omega effect
- =25: axisymm Bphi advection
- =26: axisymm Bphi diffusion
- = 27: Br production
- = 28: Br advection
- =29: Br diffusion
- = 30 : Jr
- = 31: Jr production
- =32 : Jr omega effect
- = 33: Jr advection
- = 34: Jr diffusion
- =35 : poloidal Bz production
- =36: poloidal Bz advection
- =37 : poloidal Bz diffusion
- =38 : poloidal Jz production
- =39 : poloidal Jz omega effect
- =40: poloidal Jz advection
- =41 : poloidal Jz diffusion
- =42 : toroidal Bp
- =43: toroidal Bp production
- =44: toroidal Bp omega effect
- =45: toroidal Bp advection
- =46: toroidal Bp diffusion
- =47 : phi-comp. of vorticity
- =48 : r-comp. of vorticity
- =49: toroidal Bp omega effect
- =50: toroidal Bt
- =51 : toroidal Potential
- =52 : poloidal Fieldlines in theta=const
- =53: Br dr (vp/(r sin(theta))
- =54 : phi Lorentz force
- =61: AS phi reynolds stress force
- =62 : AS phi advective stress force
- =63: AS phi viscous stress force

```
- =64 : AS phi Lorentz force
   - =66: time derivative of axisym. v phi
   - =67: relative strength of axisym. v phi
   - =81: Br inverse appearence at CMB
   - =91 : radial derivative of T
   - =92 : Vz north/south correlation
   - =93: Vorz north/south correlation
   - =94: Hel north/south correlation
   - =101: AS poloidal Br production
   - =102: AS poloidal Br dynamo term
   - =103: AS poloidal Br diffusion
   - =104: AS toroidal Bp production
   - =105: AS toroidal Bp dynamo term
   - =106: AS toroidal Bp omega effect
   - =107: AS toroidal Bp diffusion
   - = 108: Bs
• n_movie_field_start(n_field,n_movie) = defines where first element of a field is stored in frames (*)

    n_movie_field_stop(n_field,n_movie) = defines where last element of a field is stored in frames (*)
```

- The subroutine also defines appropriate file names for the movie files. These generally have the form TYPE_mov.TAG

```
Called from initialize_movie_data()
Call to delete_string(), capitalize(), abortrun(), length_to_blank(),
   str2dble()
```

subroutine movie_data/movie_gather_frames_to_rank0()

MPI communicators for movie files

```
Called from output ()
Call to abortrun()
```

10.16.3 out movie file.f90

Quick access

```
Routines get_b_surface(),
                                                   write_movie_frame(),
                                 get_fl(),
   store_movie_frame(), store_fields_sur(), get_sl(), store_fields_p(),
   store_fields_3d(), store_fields_t(), store_fields_r()
```

Needed modules

- horizontal_data (dplm(), phi(), dlh(), d_l(), theta_ord(), osnl(), o_sin_theta_e2(), o_sin_theta(), dphi(), plm(), n_theta_cal2ord(), sintheta(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel_mod (rank ()): This module contains the blocking information
- output_data (runid()): This module contains the parameters for output control
- useful (abortrun ()): library with several useful subroutines
- fields (w_rloc(), b_ic(), b_rloc(), b()): This module contains the potential fields and their radial derivatives
- fft (fft_thetab()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- out_dtb_frame(write_dtb_frame())
- lmloop_data(llmmag(), ulmmag())
- radial_data (n_r_icb()): This module defines the MPI decomposition in the radial direction.
- precision mod: This module controls the precision used in MagIC
- communications (gather_all_from_lo_to_rank0(), gt_oc())
- constants (zero(), two(), one()): module containing constants and parameters used in the code.
- num_param (tscale(), vscale()): Module containing numerical and control parameters
- physical_parameters (pr(), prmag(), lffac(), ek(), radratio(), ra()): Module containing the physical parameters
- radial_functions (orho1(), orho2(), r_cmb(), or4(), or2(), or3(), or1(), r_ic(), beta(), r(), r_surface()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (lm2(), lm21(), nfs()): Module containing blocking information
- logic(l_save_out(), l_cond_ic()): Module containing the logicals that control the run
- truncation (n_r_ic_max(), l_max(), n_r_ic_maxmag(), minc(), n_phi_max(), lm_maxmag(), l_axi(), n_r_max(), n_m_max(), lm_max(), nrp(), n_r_maxmag(), n_theta_max()): This module defines the grid points and the truncation

Variables

Subroutines and functions

```
subroutine out_movie/store_movie_frame (n_r, vr, vt, vp, br, bt, bp, sr, drsr, dvrdp, dvpdr, dvtdr, dvrdt, cvr, cbr, cbt, n_theta_start, n_theta_block, bcmb)
```

Controls output of movie frames. Usually called from radialLoop.

Parameters

```
• n_r [integer,in] :: radial grid point no.
```

```
• vr (nrp,*) [real,in]
```

- **vt** (*nrp*,*) [real,in]
- **vp** (*nrp*,*) [real,in]
- **br** (*nrp*,*) [real,in]
- **bt** (*nrp*,*) [real,in]
- **bp** (*nrp*,*) [real,in]
- **sr** (*nrp*,*) [*real*,*in*]
- drsr (nrp,*) [real,in]
- **dvrdp** (*nrp*,*) [real,in]
- **dvpdr** (*nrp*,*) [*real*,*in*]
- **dvtdr** (*nrp*,*) [real,in]
- **dvrdt** (*nrp*,*) [*real*,*in*]
- **cvr** (*nrp*,*) [real,in]
- **cbr** (*nrp*,*) [real,in]
- **cbt** (*nrp*,*) [*real*,*in*]
- n_theta_start [integer,in] :: start theta no.
- n_theta_block [integer,in] :: size of theta block
- **bcmb** (*lm_max*) [*complex*, *in*]

```
Call to store_fields_sur(), store_fields_3d(), store_fields_r(),
store_fields_t(), store_fields_p()
```

Writes different movie frames into respective output files. Called from rank 0 with full arrays in standard LM order.

- n_frame [integer,in]
- time [real,in]
- **b_lmloc** (*ulmmag-(llmmag*)+1,*n_r_maxmag*) [*complex*,*in*]
- **db_lmloc** (*ulmmag-(llmmag)+1,n_r_maxmag*) [*complex,in*]
- aj_lmloc (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **dj_lmloc** (*ulmmag-*(*llmmag*)+1,*n_r_maxmag*) [*complex*,*in*]

```
b_ic (lm_maxmag,n_r_ic_maxmag) [complex,in]
db_ic (lm_maxmag,n_r_ic_maxmag) [complex,in]
aj_ic (lm_maxmag,n_r_ic_maxmag) [complex,in]
dj_ic (lm_maxmag,n_r_ic_maxmag) [complex,in]
omega_ic [real,in]
omega_ma [real,in]
Called from output ()
Call to gather_all_from_lo_to_rank0(), abortrun(), write_dtb_frame()
subroutine out_movie/store_fields_sur(n_store_last, n_field_type, n_theta_start, n_theta_block, bcmb)
Purpose of this subroutine is to store movie frames for surfaces r=const. into array frame(,)
```

Parameters

- **n_store_last** [integer,in] :: Start position for storing -1
- n_field_type [integer,in] :: Defines field type
- n_theta_start [integer,in] :: Beginning of theta block
- n_theta_block [integer,in] :: Size of theta block
- **bcmb** (*lm_max*) [*complex*, *in*]

```
Called from store_movie_frame()
Call to get_b_surface()
```

Purpose of this subroutine is to store movie frames for surfaces r=const. into array frame(,)

- **vr** (*nrp*,*) [real,in]
- **vt** (*nrp*,*) [real,in]
- **vp** (*nrp*,*) [real,in]
- **br** (*nrp*,*) [real,in]
- **bt** (*nrp*,*) [*real*,*in*]
- **bp** (*nrp*,*) [*real*,*in*]
- **sr** (*nrp*,*) [*real*,*in*]
- **drsr** (*nrp*,*) [*real,in*]
- **dvrdp** (*nrp*,*) [*real*,*in*]
- **dvpdr** (*nrp*,*) [*real*,*in*]
- **dvtdr** (*nrp*,*) [*real*,*in*]
- dvrdt (nrp,*) [real,in]

```
• cvr (nrp,*) [real,in]
                  • n_r [integer,in]
                  • n_store_last [integer,in] :: Start position in frame(*)-1
                  • n_field_type [integer,in] :: Defines field type
                  • n_theta_start [integer,in] :: Beginning of theta block
                  • n_theta_block [integer,in] :: Size of theta block
           Called from store_movie_frame()
subroutine out_movie/store_fields_p (vr, vt, vp, br, bp, bt, sr, drsr, dvrdp, dvpdr, dvtdr, dvrdt,
                                                     cvr, cbr, cbt, n_r, n_store_last, n_field_type, n_phi_const,
                                                     n_field_size, n_theta_start, n_theta_block)
           Purpose of this subroutine is to store movie frames for surfaces phi=const. into array frames(,)
           Parameters
                  • vr (nrp,*) [real,in]
                  • vt (nrp,*) [real,in]
                  • vp (nrp,*) [real,in]
                  • br (nrp,*) [real,in]
                  • bp (nrp,*) [real,in]
                  • bt (nrp,*) [real,in]
                  • sr (nrp,*) [real,in]
                  • drsr (nrp,*) [real,in]
                  • dvrdp (nrp,*) [real,in]
```

• **dvpdr** (*nrp*,*) [*real*,*in*] • **dvtdr** (*nrp*,*) [real,in] • **dvrdt** (*nrp*,*) [real,in] • **cvr** (*nrp*,*) [real,in] • **cbr** (*nrp*,*) [*real*,*in*] • **cbt** (*nrp*,*) [*real*,*in*]

• n_r [integer,in] :: No. of radial point

• n_field_size [integer,in] :: Size of field

• **n_store_last** [integer,in] :: Start position in frame(*)-1

• n_theta_start [integer,in] :: Beginning of theta block

• n_theta_block [integer,in] :: Size of theta block

• n_field_type [integer,in] :: Defines field type • **n_phi_const** [integer,in] :: No. of surface phi Purpose of this subroutine is to store movie frames for surfaces r=const. into array frame(,)

Parameters

- **vr** (*nrp*,*) [real,in]
- **vt** (*nrp*,*) [real,in]
- **vp** (*nrp*,*) [real,in]
- **br** (*nrp*,*) [*real*,*in*]
- **bt** (*nrp*,*) [real,in]
- **bp** (*nrp*,*) [real,in]
- **sr** (*nrp*,*) [*real*,*in*]
- drsr (nrp,*) [real,in]
- **dvrdp** (*nrp*,*) [real,in]
- **dvpdr** (*nrp*,*) [*real*,*in*]
- **dvtdr** (*nrp*,*) [real,in]
- **dvrdt** (*nrp*,*) [real,in]
- **cvr** (*nrp*,*) [real,in]
- **cbt** (*nrp*,*) [real,in]
- **n_r** [integer,in] :: No. of radial grid point
- n_store_last [integer,in] :: Position in frame(*)-1
- n_field_type [integer,in] :: Defines field
- n_theta_const [integer,in] :: No. of theta to be stored
- **n_theta** [integer,in] :: No. of theta in block

Called from store_movie_frame()

Purpose of this subroutine is to store movie frames for surfaces r=const. into array frame(,)

- **vr** (*nrp*,*) [real,in]
- **vt** (*nrp*,*) [real,in]
- **vp** (*nrp*,*) [real,in]
- **br** (*nrp*,*) [*real*,*in*]
- **bt** (*nrp*,*) [real,in]
- **bp** (*nrp*,*) [real,in]
- **sr** (*nrp*,*) [*real*,*in*]

```
• drsr (nrp,*) [real,in]
```

- **dvrdp** (*nrp*,*) [real,in]
- **dvpdr** (*nrp*,*) [*real*,*in*]
- **dvtdr** (*nrp*,*) [*real*,*in*]
- **dvrdt** (*nrp*,*) [real,in]
- **cvr** (*nrp*,*) [real,in]
- **cbr** (*nrp*,*) [*real*,*in*]
- **cbt** (*nrp*,*) [real,in]
- n_r [integer,in] :: No. of radial grid point
- **n_store_last** [integer,in] :: Position in frame(*)-1
- n_field_type [integer,in] :: Defines field
- n_theta_start [integer,in] :: No. of first theta to block
- n_theta_block [integer,in] :: Size of theta block

Called from store_movie_frame()

```
subroutine out_movie/get_sl(sl, n_r, n_theta_start, n_theta_block)
```

Return field sl whose contourlines are the stream lines of the axisymmetric poloidal velocity field. sl(r,theta)=d_theta v(r,theta,m=0)/r

Parameters

- sl (*) [real,out] :: Field for field lines
- n_r [integer,in] :: No. of radial grid point
- n_theta_start [integer,in] :: No. of theta to start with
- n_theta_block [integer,in] :: Size of theta block

Called from store_fields_p()

```
subroutine out_movie/get_fl(fl, n_r, n_theta_start, n_theta_block, l_ic)
```

Return field fl whose contourlines are the fields lines of the axisymmetric poloidal mangetic field.

fl(r,theta)=d_theta b(r,theta,m=0)/r

Parameters

- fl (*) [real,out] :: Field for field lines
- n_r [integer,in] :: No. of radial grid point
- n_theta_start [integer,in] :: No. of theta to start with
- n_theta_block [integer,in] :: Size of theta block
- **l_ic** [logical,in] :: =true if inner core field

Called from store_fields_p(), store_movie_frame_ic()

subroutine out_movie/get_b_surface(b_r, b_t, b_p, bcmb, n_theta_start, n_theta_block)

Upward continuation of laplacian field to Earths surface. Field is given by poloidal harmonic coefficients b at CMB. Spherical harmonic transforms of upward continued field to r/theta/phi vector components for all logitudes and latitude are returned in br/bt/bp. Note that this routine given the real components of the magnetic fields while other transforms in the code provide only:

```
r^{**}2 br, r^{**}2 sin(theta) bt, r^{**}2 sin(theta) bp
```

Parameters

- **b r** (*nrp*,*) [real,out] :: Radial magnetic field in (phi,theta)-space
- **b_t** (*nrp*,*) [real,out] :: Latitudinal magnetic field
- **b_p** (*nrp*,*) [real,out] :: Azimuthal magnetic field.
- **bcmb** (*lm_max*) [*complex*,*in*]
- n_theta_start [integer,in] :: No. of theta to start with
- n_theta_block [integer,in] :: Size of theta block

```
Called from store_fields_sur()
Call to fft_thetab()
```

10.16.4 store movie IC.f90

Quick access

```
Routines store_movie_frame_ic()
```

- horizontal_data (dplm(), plm(), dlh(), n_theta_cal2ord(), o_sin_theta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- movie_data (n_movie_fields_ic(), n_movies(), n_movie_field_stop(), n_movie_surface(), n_movie_field_type(), n_movie_field_start(), n_movie_fields(), n_movie_const(), frames(), n_movie_type())
- out_movie(get_fl())
- fft (fft_thetab()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- legendre_spec_to_grid(legtf())
- radial data(n r icb()): This module defines the MPI decomposition in the radial direction.
- precision_mod: This module controls the precision used in MagIC
- logic (l_cond_ic()): Module containing the logicals that control the run
- physical_parameters (lffac()): Module containing the physical parameters
- truncation (n_r_ic_max(), lm_maxmag(), n_r_ic_maxmag(), minc(), n_phi_max(), l_max(), l_axi(), lm_max(), nrp(), n_r_maxmag(), n_theta_max()): This module defines the grid points and the truncation
- leg_helper_mod(legprep_ic())
- blocking (nthetabs(), nfs(), sizethetab()): Module containing blocking information

- constants (one ()): module containing constants and parameters used in the code.
- radial_functions (r_icb(), r_ic(), o_r_ic2(), o_r_ic()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Subroutines and functions

```
subroutine out_movie_ic/store_movie_frame_ic (bicb, b_ic, db_ic, ddb_ic, aj_ic, dj_ic)

Controls storage of IC magnetic field in movie frame.
```

Parameters

- **bicb** (*lm_maxmag*) [*complex*,*in*]
- **b_ic** (lm_maxmag,n_r_ic_maxmag) [complex,in]
- **db_ic** (lm_maxmag,n_r_ic_maxmag) [complex,in]
- **ddb_ic** (lm_maxmag,n_r_ic_maxmag) [complex,in]
- aj_ic (lm_maxmag,n_r_ic_maxmag) [complex,in]
- **dj_ic** (lm_maxmag,n_r_ic_maxmag) [complex,in]

```
Called from output()
Call to legprep_ic(), legtf(), fft_thetab(), get_fl()
```

10.16.5 out coeff.f90

Description

This module contains the subroutines that calculate the Bcmb files, the [BIVIT]_coeff_r files and the [BIVIT]_Imr files

Quick access

```
Routines finalize_coeffs(), initialize_coeffs(), write_pot(), write_bcmb(),
    write_coeff_r()
```

- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- output_data (tag()): This module contains the parameters for output control
- lmloop_data(llm(), ulm())
- precision_mod: This module controls the precision used in MagIC
- communications(gather_from_lo_to_rank0())
- parallel_mod (rank ()): This module contains the blocking information

- logic(l_save_out(), l_cmb_field(), l_r_field(), l_average(), l_cond_ic()): Module containing the logicals that control the run
- physical_parameters (pr(), prmag(), ek(), sigma_ratio(), radratio(), ra()): Module containing the physical parameters
- truncation (lm_max(), n_r_ic_max(), l_max(), minc(), n_r_max()): This module defines the grid points and the truncation
- blocking (1m2()): Module containing blocking information
- constants (two (), half ()): module containing constants and parameters used in the code.
- radial_functions (r(), rho0()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

- out_coeff/work (:) [complex,private/allocatable]
- out_coeff/filehandle [integer,private]

Subroutines and functions

Each call of this subroutine writes time and the poloidal magnetic potential coefficients b at the CMB up to degree and order l_max_cmb at the end of output file \$cmb_file. The parameters l_max_cmb, minc and the number of stored coeffs. are written into the first line of \$cmb_file. Each further set contains:

```
time,
real(b(l=0,m=0)),imag(b(l=0,m=0)),
real(b(l=1,m=0)),imag(b(l=1,m=0)),
```

Real and imaginary part of b(*) for all orders $m \le 1$ are written for a specific degree 1, then for the degrees l+1, l+2, l_max_cmb .

Parameters

- **time** [real,in] :: Time
- **b_lmloc** (*ulm*-(*llm*)+1) [*complex*,*in*]
- l_max_cmb [integer,inout] :: Max degree of output
- n_cmb_sets [integer,inout] :: Total no. of cmb sets,
- cmb_file [character,in] :: Name of output file
- **n_cmb_file** [integer,inout] :: Output unit for \$cmb_file

Called from fields_average(), output()

```
Call to gather_from_lo_to_rank0()
```

Each call of this subroutine writes time and the poloidal and toroidal coeffitients w,dw,z at a specific radius up to degree and order l_max_r at the end of output file \$file. If the input is magnetic field (nVBS=2) ddw is stored as well. If the input is entropy field (nVBS=3) only ddw=s is stored. The parameters l_max_r, minc, the number of stored coeffs and radius in the outer core are written into the first line of \$file. Each further set contains:

```
time,
real(w(l=0,m=0)), imag(w(l=0,m=0)),
real(w(l=1,m=0)), imag(w(l=1,m=0)),
...
real(dw(l=0,m=0)), imag(dw(l=0,m=0)),
real(dw(l=1,m=0)), imag(dw(l=1,m=0)),
...
real(z(l=0,m=0)), imag(z(l=0,m=0)),
real(z(l=1,m=0)), imag(z(l=1,m=0)),
...
real(ddw(l=0,m=0)), imag(ddw(l=0,m=0)),
real(ddw(l=1,m=0)), imag(ddw(l=1,m=0)),
```

Real and imaginary part of w(*) for all orders $m \le 1$ are written for a specific degree 1, then for the degrees 1+1, 1+2, 1 - max r.

Parameters

- **time** [real,in] :: Time
- w lmloc (ulm-(llm)+1) [complex,in]
- **dw_lmloc** (*ulm*-(*llm*)+1) [complex,in]
- **ddw_lmloc** (*ulm*-(*llm*)+1) [*complex*,*in*]
- **z_lmloc** (*ulm*-(*llm*)+1) [*complex*,*in*]
- **r** [real,in] :: radius of coeffs
- l_max_r [integer,inout] :: Max degree of output
- **n_sets** [integer,inout] :: Total no. of cmb sets,
- **file** [character,in] :: Name of output file
- **n** file [integer,inout] :: Output unit for \$file
- **nvbs** [integer,in] :: True if output is flow

```
Called from output ()
```

```
Call to gather from lo to rank0()
```

subroutine out_coeff/write_pot(time, b, aj, b_ic, aj_ic, npotsets, root, omega_ma, omega_ic)

This routine stores the fields in spectral and radial space

- time [real,in]
- **b** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]

```
• aj (ulm-(llm)+1,n\_r\_max) [complex,in]
```

- **b_ic** (*ulm*-(*llm*)+1,*n_r_ic_max*) [*complex*,*in*]
- **aj_ic** (*ulm*-(*llm*)+1,*n_r_ic_max*) [*complex*,*in*]
- **npotsets** [integer,inout]
- **root** [character,in]
- omega ma [real,in]
- omega_ic [real,in]

```
Called from fields_average(), output()
Call to gather from lo to rank0()
```

10.16.6 field_average.f90

Description

This module is used when one wants to store time-averaged quantities

Quick access

```
Variables aj_ave_global, b_ave_global, db_ave_global, dw_ave_global,
    p_ave_global, s_ave_global, w_ave_global, xi_ave_global, z_ave_global,
    aj_ave, aj_ic_ave, b_ave, b_ic_ave, p_ave, s_ave, w_ave, xi_ave, z_ave

Routines finalize_fields_average_mod(), initialize_fields_average_mod(),
    fields_average()
```

- horizontal_data (dplm(), plm(), dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- fft (fft_thetab()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- lmloop_data(ulmmag(), llmmag(), llm(), ulm())
- radial_der_even(get_drns_even(), get_ddrns_even())
- radial der (get dr ()): Radial derivatives functions
- graphout_mod (graphout (), graphout_ic()): This module contains the subroutines that store the 3-D graphic files.
- magnetic_energy (get_e_mag())
- parallel mod (rank ()): This module contains the blocking information
- radial_functions (dr_fac_ic(), r(), chebt_ic(), rscheme_oc(), chebt_ic_even()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- leg_helper_mod(legprep())

- fieldslast (dbdt_iclast_lmloc(), dzdtlast_lo(), djdtlast_lmloc(), djdt_iclast_lmloc(), dpdtlast_lmloc(), dxidtlast_lmloc(), dwdtlast_lmloc(), dsdtlast_lmloc(), dbdtlast_lmloc()): This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- storecheckpoints (store()): This module contains several subroutines that can be used to store the checkpoint_#.tag files
- kinetic_energy (get_e_kin())
- out_coeff (write_pot(), write_bcmb()): This module contains the subroutines that calculate the Bcmb files, the [BIVIT]_coeff_r files and the [BIVIT]_lmr files
- blocking (lmstartb(), lm2(), nthetabs(), sizethetab(), nfs(), lmstopb()): Module containing blocking information
- constants (zero(), vol_ic(), vol_oc(), one()): module containing constants and parameters used in the code.
- truncation: This module defines the grid points and the truncation
- precision_mod: This module controls the precision used in MagIC
- output_data (l_max_cmb(), n_graphs(), n_log_file(), n_graph_file(), tag(), graph_file(), log_file()): This module contains the parameters for output control
- spectra(spectrum(), spectrum_temp())
- legendre_spec_to_grid(legtf())
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- communications (get_global_sum(), gather_from_lo_to_rank0(), gather_all_from_lo_to_rank0(), gt_ic(), gt_oc())
- logic(l_chemical_conv(), l_mag(), l_heat(), l_save_out(), l_cond_ic(), l_conv()): Module containing the logicals that control the run

- fields_average_mod/**z_ave**(:,:) [complex,private/allocatable]
- fields average mod/b ic ave(:,:) [complex,private/allocatable]
- fields_average_mod/db_ave_global(:) [complex,private/allocatable]
- fields_average_mod/**s_ave_global** (:) [complex,private/allocatable]
- fields_average_mod/bicb(:) [complex,private/allocatable]
- fields_average_mod/**p_ave** (:,:) [complex,private/allocatable]
- fields_average_mod/b_ave(:,:) [complex,private/allocatable]
- fields_average_mod/w_ave_global(:) [complex,private/allocatable]
- fields_average_mod/w_ave(:,:) [complex,private/allocatable]
- fields_average_mod/aj_ave(:,:) [complex,private/allocatable]
- fields_average_mod/**p_ave_global** (:) [complex,private/allocatable]

- fields_average_mod/z_ave_global(:) [complex,private/allocatable]
- fields_average_mod/b_ave_global (:) [complex,private/allocatable]
- fields_average_mod/**s_ave** (:,:) [complex,private/allocatable]
- fields_average_mod/xi_ave(:,:) [complex,private/allocatable]
- fields_average_mod/xi_ave_global(:) [complex,private/allocatable]
- fields_average_mod/aj_ave_global(:) [complex,private/allocatable]
- fields_average_mod/aj_ic_ave(:,:) [complex,private/allocatable]
- fields_average_mod/dw_ave_global(:) [complex,private/allocatable]

Subroutines and functions

This subroutine averages fields b and v over time.

- simtime [real,in]
- **dt** [real,in]
- dtnew [real,in]
- nave [integer,in] :: number for averaged time steps
- **l_stop_time** [logical,in] :: true if this is the last time step
- **time_passed** [real,in] :: time passed since last log
- **time_norm** [real,in] :: time passed since start of time loop
- omega_ic [real,in]
- omega_ma [real,in]
- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- \mathbf{z} (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **p** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- \mathbf{s} (ulm-(llm)+1,n_r_max) [complex,in]
- **xi** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **b** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **aj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **b_ic** (*ulmmag-(llmmag)+1,n_r_ic_maxmag*) [*complex,in*]

• aj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,in]

Called from output ()

```
Call to get_ddrns_even(), get_drns_even(), spectrum(), spectrum_temp(),
    get_e_kin(), get_e_mag(), graphout(), gather_from_lo_to_rank0(),
    legprep(), legtf(), fft_thetab(), gather_all_from_lo_to_rank0(),
    graphout_ic(), write_bcmb(), write_pot(), store()
```

10.17 IO: RMS force balance, torsional oscillations, misc

10.17.1 RMS.f90

Description

This module contains the calculation of thr RMS force balance and induction terms.

Quick access

Variables n_dtbrms_file, n_dtvrms_file, n_cheb_maxc, ncut, n_r_maxc, dtbrms_file, dtvrms_file, advrmsl_sd, advrmsl_ta, advrmsd, arcmagrmsl_sd, arcmagrmsl_ta, arcmagrmssd, arcrmsl_sd, arcrmsl_ta, arcrmssd, buormsl_sd, buormsl_ta, buormssd, ciarmsl_sd, ciarmsl_ta, ciarmssd, clfrmsl_sd, clfrmsl_ta, clfrmssd, corrmsl_sd, corrmsl_ta, corrmssd, difrmsl_sd, difrmsl_ta, difrmssd, dtvrmsl_sd, dtvrmsl_ta, dtvrmssd, geormsl_sd, geormsl_ta, geormssd, lfrmsl_sd, lfrmsl_ta, lfrmssd, magrmsl_sd, magrmsl_ta, magrmssd, plfrmsl_sd, plfrmsl_ta, plfrmssd, prermsl_sd, prermsl_ta, prermssd, rc, dr_facc, adv2hint, arc2hint, arcmag2hint, buo2hint, cia2hint, clf2hint, cor2hint, difpollmr, dtbpollmr, dtbpollmr, dtbpollmr, dtbpollhint, dtbtor2hint, dtvpollhint, dtvtor2hint

- chebyshev(type_cheb_odd())
- horizontal_data (phi(), theta_ord()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- useful (abortrun (), get_mean_sd()): library with several useful subroutines
- lmloop_data(ulmmag(), llmmag(), llm(), ulm())
- radial_der (get_dr()): Radial derivatives functions
- cosine_transform_odd
- radial_scheme (type_rscheme()): This is an abstract type that defines the radial scheme used in MagIC
- integration (rint_r()): Radial integration functions
- parallel mod: This module contains the blocking information

- num_param (alph1(), alph2(), tscale()): Module containing numerical and control parameters
- physical_parameters(pr(), prmag(), radratio(), ra(), ek()): Module containing the physical parameters
- truncation (l_max(), minc(), n_phi_max(), lm_maxmag(), n_r_max_dtb(), n_r_max(), fd_stretch(), lm_max_dtb(), lm_max(), n_cheb_max(), n_r_maxmag(), fd_ratio(), n_theta_max()): This module defines the grid points and the truncation
- finite_differences (type_fd()): This module is used to calculate the radial grid when finite differences are requested
- precision_mod: This module controls the precision used in MagIC
- rms_helpers (hint2dpollm(), get_poltorrms(), hint2dpol(), get_ras(), get_paslm()): This module contains several useful subroutines required to compute RMS diagnostics
- blocking (lm2(), nthetabs(), sizethetab(), lm2m(), nfs(), lo_map(), st_map()): Module containing blocking information
- constants (third(), one(), four(), zero(), half(), vol_oc(), pi()): module containing constants and parameters used in the code.
- radial_functions (r_cmb(), r_icb(), rscheme_oc(), r()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- output_data (tag(), rdea(), runid(), rcut()): This module contains the parameters for output control
- dtb_mod (pdiflm_lmloc(), tstrlm_lmloc(), tdiflm_lmloc(), pstrlm_lmloc(), tadvlm_lmloc(), tomelm_lmloc(), padvlm_lmloc()): This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output....
- radial_data (nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- logic(l_finite_diff(), l_newmap(), l_corr(), l_heat(), l_mag_lf(), l_save_out(), l_mag(), l_conv_nl(), l_conv()): Module containing the logicals that control the run

- rms/buormsl sd(:) [real,private/allocatable]
- rms/dtbpol2hint(:,:,:) [real,allocatable/public]
- rms/geo2hint (:,:) [real,allocatable/public]
- rms/dtvrmssd(:) [real,private/allocatable]
- rms/corrmsl_ta(:)[real,private/allocatable]
- rms/dtvtor2hint (:,:,:) [real,allocatable/public]
- rms/advrmsl_ta(:)[real,private/allocatable]
- rms/cia2hint (:,:) [real,allocatable/public]
- rms/plfrmsl sd(:) [real,private/allocatable]

- rms/ncut [integer,public]

 Number of points for the cut-off
- rms/arcmagrmsl_sd(:) [real,private/allocatable]
- rms/advrmsl_sd(:) [real,private/allocatable]
- rms/dtbpollmr(:,:) [complex,allocatable/public]
- rms/diftor2hint (:,:,:) [real,allocatable/public]
- rms/lfrmssd(:) [real,private/allocatable]
- rms/dtvrmsl_sd(:) [real,private/allocatable]
- rms/prermssd(:) [real,private/allocatable]
- rms/lf2hint (:,:) [real,allocatable/public]
- rms/ciarmsl_ta(:)[real,private/allocatable]
- rms/buormssd(:) [real,private/allocatable]
- rms/corrmssd(:) [real,private/allocatable]
- rms/plfrmsl_ta(:) [real,private/allocatable]
- rms/magrmsl_sd(:) [real,private/allocatable]
- rms/geormsl_ta(:)[real,private/allocatable]
- rms/dtbrms_file [character,private]
- rms/advrmssd(:) [real,private/allocatable]
- rms/dtvpollmr(:,:) [complex,allocatable/public]
- rms/n_dtvrms_file [integer,private]
- rms/plfrmssd(:) [real,private/allocatable]
- rms/dtvrmsl_ta(:)[real,private/allocatable]
- rms/arc2hint (:,:) [real,allocatable/public]
- rms/clfrmssd(:) [real,private/allocatable]
- rms/dtbtor2hint (:,:,:) [real,allocatable/public]
- rms/buormsl_ta(:)[real,private/allocatable]
- rms/arcmag2hint (:,:) [real,allocatable/public]
- rms/clfrmsl_ta(:) [real,private/allocatable]
- rms/arcrmssd(:) [real,private/allocatable]
- rms/adv2hint (:,:) [real,allocatable/public]
- rms/clf2hint (:,:) [real,allocatable/public]
- rms/difpol2hint (:,:,:) [real,allocatable/public]
- rms/n_cheb_maxc [integer,public]
 Number of Chebyshevs
- rms/lfrmsl_sd(:) [real,private/allocatable]
- rms/arcrmsl_sd(:) [real,private/allocatable]
- rms/geormsl_sd(:) [real,private/allocatable]

```
• rms/ciarmsl_sd(:) [real,private/allocatable]
• rms/dr_facc(:) [real, allocatable/public]
• rms/dtvpol2hint(:,:,:) [real,allocatable/public]
• rms/difrmssd(:) [real,private/allocatable]
• rms/n dtbrms file[integer,private]
• rms/clfrmsl_sd(:) [real,private/allocatable]
• rms/prermsl_ta(:) [real,private/allocatable]
• rms/ciarmssd(:) [real,private/allocatable]
• rms/rc(:) [real,private/allocatable]
• rms/buo2hint (:,:) [real,allocatable/public]
• rms/difrmsl_ta(:)[real,private/allocatable]
• rms/difpollmr(:,:) [complex,allocatable/public]
• rms/prermsl_sd(:) [real,private/allocatable]
• rms/arcmagrmsl_ta(:) [real,private/allocatable]
• rms/lfrmsl_ta(:) [real,private/allocatable]
• rms/arcmagrmssd(:) [real,private/allocatable]
• rms/cor2hint (:,:) [real,allocatable/public]
• rms/mag2hint (:,:) [real,allocatable/public]
• rms/arcrmsl_ta(:) [real,private/allocatable]
• rms/plf2hint (:,:) [real,allocatable/public]
• rms/magrmsl_ta(:)[real,private/allocatable]
• rms/pre2hint (:,:) [real,allocatable/public]
• rms/eps[real,private/parameter=10.0_cp*epsilon(one)]
• rms/magrmssd(:) [real,private/allocatable]
• rms/difrmsl_sd(:) [real,private/allocatable]
• rms/geormssd(:) [real,private/allocatable]
• rms/dtvrms_file [character,private]
• rms/n_r_maxc[integer,public]
      Number of radial points
• rms/corrmsl_sd(:) [real,private/allocatable]
```

Subroutines and functions

```
subroutine rms/initialize_rms()
    Memory allocation
    Called from magic
    Call to init rnb()
```

```
called from magic
subroutine rms/zerorms()
Zeros integrals that are set in get_td, update_z, update_wp, update_b, dtVrms and dtBrms
Called from output()
subroutine rms/init_rnb(r, rcut, rdea, r2, n_r_max2, n_cheb_max2, ns, rscheme_rms)
```

Prepares the usage of a cut back radial grid where nS points on both boundaries are discarded. The aim actually is to discard boundary effects, but just not considering the boundary grid points does not work when you also want radial derivatives and integrals. For these we use the Chebychev transform which needs are particular number of grid points so that the fast cosine transform can be applied. Therefor more than just 2 points have to be thrown away, which may make sense anyway.

Parameters

- **r** (*n_r_max*) [real,in]
- rcut [real,in]
- rdea [real,in]
- r2 (*) [real,out,allocatable]
- n_r_max2 [integer,out]
- n_cheb_max2 [integer,out]
- **ns** [integer,out]
- rscheme_rms [real]

Called from initialize_rms()

Call to abortrun()

subroutine rms/dtvrms (time, nrms_sets, timepassed, timenorm)

This routine calculates and stores the different contributions of the forces entering the Navier-Stokes equation.

Parameters

- time [real,in]
- nrms_sets [integer,inout]
- timepassed [real,in]
- timenorm [real,in]

```
Called from output ()
```

Call to hint2dpol(), rint_r()

subroutine rms/dtbrms(time)

Parameters time [real,in]

Called from output ()

Call to get poltorrms(), hint2dpollm(), rint r()

10.17.2 RMS_helpers.f90

Description

This module contains several useful subroutines required to compute RMS diagnostics

Quick access

```
Routines get_ras(), hint2dpollm(), hint2dpol(), hintrms(), get_poltorrms(), hint2pollm(), hint2pol(), get_paslm(), hint2torlm(), hint2tor()
```

Needed modules

- horizontal_data(osn1(), plm(), dlh(), dplm()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel_mod: This module contains the blocking information
- useful (cc2real ()): library with several useful subroutines
- integration (rint_r()): Radial integration functions
- precision_mod: This module controls the precision used in MagIC
- truncation(lm_max(), l_max(), n_r_max(), lm_max_dtb()): This module defines the grid points and the truncation
- lmmapping (mappings())
- blocking (lm2(), st_map()): Module containing blocking information
- constants (vol_oc(), one()): module containing constants and parameters used in the code.
- radial_functions (rscheme_oc(), r(), or2()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

Subroutines and functions

```
subroutine rms_helpers/get_paslm(tlm, bp, rt, nthetastart, sizethetablock)
```

Purpose of this subroutine is to calculated the axisymmetric phi component Bp of an axisymmetric toroidal field Tlm given in spherical harmonic space (l,m=0).

- tlm (lm_max_dtb) [complex,in] :: field in (l,m)-space for rT
- **bp** (*) [real,out]
- **rt** [real,in] :: radius
- **nthetastart** [integer,in] :: first theta to be treated
- **sizethetablock** [integer,in] :: size of theta block

calculates integral PolRms=sqrt(Integral (pol^2 dV)) calculates integral TorRms=sqrt(Integral (tor^2 dV)) plus axisymmetric parts. integration in theta,phi by summation of spherical harmonics integration in r by using Chebycheff integrals The mapping map gives the mapping Im to l,m for the input arrays Pol,drPol and Tor Output: PolRms,TorRms,PolAsRms,TorAsRms

Parameters

```
• pol (ulm-llm+1,n_r_max) [complex,in]
```

- **drpol** (*ulm-llm*+1,*n_r_max*) [*complex*,*in*]
- **tor** (*ulm-llm*+1,*n_r_max*) [*complex*,*in*]
- **llm** [integer,in]
- **ulm** [integer,in] :: Toroidal field Potential
- polrms [real,out]
- torrms [real, out]
- polasrms [real,out]
- torasrms [real,out]
- map [mappings,in]

```
Called from dtbrms()
```

Call to cc2real(), rint_r()

subroutine rms_helpers/hint2dpol(dpol, lmstart, lmstop, pol2hint, map)

Parameters

- **dpol** (lmstop-lmstart+1) [complex,in]
- **Imstart** [integer,in]
- **Imstop** [integer,in] :: Toroidal field Potential
- **pol2hint** (*l_max*)+1) [*real,inout*]
- map [mappings,in]

Called from dtvrms()

Call to cc2real()

subroutine rms_helpers/hint2dpollm(dpol, lmstart, lmstop, pol2hint, map)

Parameters

- **dpol** (lmstop-lmstart+1) [complex,in]
- **Imstart** [integer,in]
- **lmstop** [integer,in]
- **pol2hint** (lmstop-lmstart+1) [real,inout]
- map [mappings,in]

Called from dtbrms()

Call to cc2real()

```
subroutine rms_helpers/hint2pol(pol, lb, ub, nr, lmstart, lmstop, pollmr, pol2hint, map)
          Parameters
                 • pol (ub-lb+1) [complex,in]
                 • lb [integer,in]
                 • ub [integer,in] :: Poloidal field Potential
                 • nr [integer,in]
                 • Imstart [integer,in]
                 • lmstop [integer,in]
                 • pollmr (ub-lb+1) [complex,out]
                 • pol2hint (l_max)+1) [real,inout]
                 • map [mappings,in]
           Called from updatewpt(), updatewps(), updatewp()
           Call to cc2real()
subroutine rms_helpers/hint2pollm(pol, lb, ub, nr, lmstart, lmstop, pollmr, pol2hint, map)
           Parameters
                 • pol (ub-lb+1) [complex,in]
                 • lb [integer,in]
                 • ub [integer,in] :: Poloidal field Potential
                 • nr [integer,in]
                 • Imstart [integer,in]
                 • lmstop [integer,in]
                 • pollmr (ub-lb+1) [complex,out]
                 • pol2hint (ub-lb+1) [real,inout]
                 • map [mappings,in]
           Called from updateb()
           Call to cc2real()
subroutine rms_helpers/hintrms (f, nr, lmstart, lmstop, lmp, f2hint, map, sphertor)
           Parameters
                 • f (*) [complex,in]
                 • nr [integer,in]
                 • Imstart [integer,in]
                 • lmstop [integer,in]
                 • lmp [integer,in]
                 • f2hint (l_max)+1) [real,inout]
                 • map [mappings,in]
                 • sphertor [logical,in]
```

```
Called from get_td()
           Call to cc2real()
subroutine rms_helpers/hint2tor(tor, lb, ub, nr, lmstart, lmstop, tor2hint, map)
           Parameters
                 • tor (ub-lb+1) [complex,in]
                 • lb [integer,in]
                 • ub [integer,in] :: Toroidal field Potential
                 • nr [integer,in]
                 • Imstart [integer,in]
                 • lmstop [integer,in]
                 • tor2hint (l_max)+1) [real,inout]
                 • map [mappings,in]
           Called from updatez()
           Call to cc2real()
subroutine rms_helpers/hint2torlm(tor, lb, ub, nr, lmstart, lmstop, tor2hint, map)
           Parameters
                 • tor (ub-lb+1) [complex,in]
                 • lb [integer,in]
                 • ub [integer,in] :: Toroidal field Potential
                 • nr [integer,in]
                 • Imstart [integer,in]
                 • lmstop [integer,in]
                 • tor2hint (ub-lb+1) [real,inout]
                 • map [mappings,in]
           Called from updateb()
           Call to cc2real()
subroutine rms_helpers/get_ras (blm, br, rt, nthetastart, sizethetablock)
           Purpose of this subroutine is to calculate the axisymmetric radial component Br of an axisymmetric
           ploidal field Blm given in spherical harmonic space (1,m=0).
           Parameters
                 • blm (lm_max_dtb) [complex,in] :: field in (l,m)-space for rT
                 • br (*) [real,out]
```

• **nthetastart** [integer,in] :: first theta to be treated

• **sizethetablock** [integer,in] :: last theta

• **rt** [real,in] :: radius

10.17.3 dtB.f90

Description

This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output.

Quick access

```
Variables r2lo_dtb, padvlm, padvlmic, padvlmic_lmloc, pdiflm, pdiflm_lmloc, pdiflmic, pdiflmic_lmloc, pstrlm, tadvlm, tadvlmic, tadvlmic_lmloc, tdiflm, tdiflm_lmloc, tdiflmic, tdiflmic_lmloc, tomelm, tstrlm, padvlm_rloc, pstrlm_rloc, tadvlm_rloc, tadvrlm_rloc, tomelm_rloc, tomerlm_rloc, tstrlm_rloc, tstrrlm_rloc, padvlm_lmloc, pstrlm_lmloc, tadvlm_lmloc, tadvrlm_lmloc, tomelm_lmloc, tomerlm_lmloc, tstrrlm_lmloc, tstrrlm_lmloc, tstrrlm_lmloc, tstrrlm_lmloc, dtb_lmloc_container, dtb_rloc_container
```

```
Routines dtb_gather_lo_on_rank0(), dtb_from_rloc_to_lo(), initialize_dtb_mod(), finalize_dtb_mod(), get_dh_dtblm(), get_dtblm(), get_dtblmfinish()
```

- horizontal_data (hdif_b(), osn1(), osn2(), dlh(), cosn2(), d_lp1(), dtheta1s(), dphi(), dtheta1a()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel_mod: This module contains the blocking information
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- fft: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- lmloop_data(ulm(), llmmag(), llm(), ulmmag())
- radial_spectra
- radial_data (nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- precision mod: This module controls the precision used in MagIC
- communications (gather_all_from_lo_to_rank0(), r2lo_redist_start(), create_r2lm_type(), destroy_r2lm_type(), gt_oc(), gt_ic(), r2lm_type(), r2lo_redist_wait())
- legendre_grid_to_spec(legtf2(), legtf3())
- logic(l_dtbmovie(), l_cond_ic(), l_dtrmagspec()): Module containing the logicals that control the run
- radial_der (get_dr()): Radial derivatives functions
- physical_parameters (opm(), o_sr()): Module containing the physical parameters

- radial_functions (rscheme_oc(), orho1(), or2(), or1(), dllambda(), o_r_ic(), lambda()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (121mas(), 1m21mp(), 1m2m(), 1m21(), nfs(), 1mp21mps(), 1o_map(), 1mp21mpa(), st_map()): Module containing blocking information
- constants (two ()): module containing constants and parameters used in the code.
- truncation(n_r_ic_max(), 1_max(), n_r_ic_maxmag(), n_r_ic_max_dtb(), ldtbmem(), n_phi_max(), n_r_max_dtb(), 1_axi(), n_r_max(), lm_max_dtb(), lm_max(), nrp(), n_cheb_max(), n_r_maxmag()): This module defines the grid points and the truncation

- dtb_mod/tstrlm_lmloc(:,:) [complex,pointer/public]
- dtb_mod/tadvlmic(:,:) [complex,allocatable/public]
- dtb mod/tomerlm lmloc(:,:) [complex,pointer/public]
- dtb_mod/pstrlm_lmloc(:,:) [complex,pointer/public]
- dtb_mod/tadvlmic_lmloc(:,:) [complex,allocatable/public]
- dtb_mod/tadvlm_rloc(:,:) [complex,private/pointer]
- dtb_mod/padvlm(:,:) [complex,allocatable/public]
- dtb_mod/padvlm_lmloc(:,:) [complex,pointer/public]
- dtb_mod/pdiflmic(:,:) [complex,allocatable/public]
- dtb_mod/tstrlm(:,:) [complex,allocatable/public]
- dtb_mod/tomelm_lmloc(:,:) [complex,pointer/public]
- dtb_mod/dtb_lmloc_container (:,:,:) [complex,private/target/allocatable]
- dtb_mod/tdiflm(:,:) [complex,allocatable/public]
- dtb_mod/tadvrlm_lmloc(:,:) [complex,pointer/public]
- dtb_mod/tdiflmic(:,:) [complex,allocatable/public]
- dtb_mod/tadvlm(:,:) [complex,allocatable/public]
- dtb_mod/tdiflm_lmloc(:,:) [complex,allocatable/public]
- dtb mod/tadvlm lmloc(:,:) [complex,pointer/public]
- dtb_mod/tstrlm_rloc(:,:) [complex,private/pointer]
- dtb_mod/tadvrlm_rloc(:,:) [complex,private/pointer]
- dtb_mod/padvlmic(:,:) [complex,allocatable/public]
- dtb_mod/dtb_rloc_container (:,:,:) [complex,private/target/allocatable]
- dtb_mod/pdiflm_lmloc(:,:) [complex,allocatable/public]
- dtb_mod/tdiflmic_lmloc(:,:) [complex,allocatable/public]
- dtb_mod/tstrrlm_lmloc(:,:) [complex,pointer/public]
- dtb_mod/pdiflmic_lmloc(:,:) [complex,allocatable/public]

- dtb_mod/pstrlm(:,:) [complex,allocatable/public]
- dtb_mod/pstrlm_rloc(:,:) [complex,private/pointer]
- dtb_mod/tstrrlm_rloc(:,:) [complex,private/pointer]
- dtb_mod/tomelm_rloc(:,:) [complex,private/pointer]
- dtb_mod/padvlmic_lmloc(:,:) [complex,allocatable/public]
- dtb_mod/r2lo_dtb [r2lm_type,private]
- dtb_mod/tomerlm_rloc(:,:) [complex,private/pointer]
- dtb_mod/pdiflm(:,:) [complex,allocatable/public]
- dtb_mod/padvlm_rloc(:,:) [complex,private/pointer]
- dtb_mod/tomelm(:,:) [complex,allocatable/public]

Subroutines and functions

```
subroutine dtb_mod/initialize_dtb_mod()
     Memory allocation
         Called from magic
         Call to create r2lm type()
subroutine dtb_mod/finalize_dtb_mod()
         Called from magic
         Call to destroy_r2lm_type()
subroutine dtb mod/dtb from rloc to lo()
     MPI transpose (from LM to R ) for dtB calculations
         Called from get_dtblmfinish()
         Call to r2lo_redist_start(), r2lo_redist_wait()
subroutine dtb mod/dtb gather lo on rank0()
     MPI gather on rank0 for dtBmovie outputs. This routine should really be suppressed once the movie outputs
     have been improved
         Called from get_dtblmfinish()
         Call to gather_all_from_lo_to_rank0()
subroutine dtb_mod/get_dtblm(nr, vr, vt, vp, br, bt, bp, n_theta_start, n_theta_block, btvrlm,
                                   bpvrlm, brvtlm, brvplm, btvplm, bpvtlm, brvzlm, btvzlm, btvpcotlm,
                                   bpvtcotlm, btvzcotlm, btvpsn2lm, bpvtsn2lm, btvzsn2lm)
```

- **nr** [integer,in]
- **vr** (nrp,nfs) [real,in]
- **vt** (*nrp*,*nfs*) [*real*,*in*]
- **vp** (*nrp*,*nfs*) [real,in]
- **br** (*nrp*,*nfs*) [real,in]
- **bt** (*nrp*,*nfs*) [*real*,*in*]

- **bp** (*nrp*,*nfs*) [real,in]
- n_theta_start [integer,in]
- n_theta_block [integer,in]
- **btvrlm** (*) [complex,out]
- **bpvrlm** (*) [complex,out]
- **brvtlm** (*) [complex,out]
- **brvplm** (*) [complex,out]
- **btvplm** (*) [complex,out]
- **bpvtlm** (*) [complex,out]
- brvzlm (*) [complex,out]
- **btvzlm** (*) [complex,out]
- **btvpcotlm** (*) [complex,out]
- **bpvtcotlm** (*) [complex,out]
- **btvzcotlm** (*) [complex,out]
- btvpsn2lm (*) [complex,out]
- bpvtsn2lm (*) [complex,out]
- btvzsn2lm (*) [complex,out]

 $\begin{tabular}{ll} \textbf{Called from} & do_iteration_thetablocking_openmp(), do_iteration_thetablocking_seq(), \\ & do_iteration_thetablocking_shtns() \end{tabular}$

```
Call to fft_thetab(), legtf3(), legtf2()
```

subroutine dtb_mod/**get_dh_dtblm** (*nr*, *btvrlm*, *bpvrlm*, *brvtlm*, *brvplm*, *btvplm*, *bpvtsn2lm*) *zlm*, *btvpcotlm*, *bpvtcotlm*, *btvpsn2lm*)

Purpose of this routine is to calculate theta and phi derivative related terms of the magnetic production and advection terms and store them.

- **nr** [integer,in]
- **btvrlm** (*) [complex,in]
- **bpvrlm** (*) [complex,in]
- **brvtlm** (*) [complex,in]
- **brvplm** (*) [complex,in]
- **btvplm** (*) [complex,in]
- **bpvtlm** (*) [complex,in]
- brvzlm (*) [complex,in]
- btvzlm (*) [complex,in]
- btvpcotlm (*) [complex,in]
- **bpvtcotlm** (*) [complex,in]
- btvpsn2lm (*) [complex,in]

• bpvtsn2lm (*) [complex,in]

subroutine dtb_mod/**get_dtblmfinish**(*time*, *n_time_step*, *omega_ic*, *b*, *ddb*, *aj*, *dj*, *ddj*, *b_ic*, *db_ic*, *dd_ic*, *aj_ic*, *dj_ic*, *ddj_ic*, *l_frame*)

Parameters

- time [real,in]
- n_time_step [integer,in]
- omega_ic [real,in]
- **b** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **ddb** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **aj** (*ulmmag-*(*llmmag*)+1,*n_r_maxmag*) [*complex*,*in*]
- **dj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **ddj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **b_ic** (*ulmmag-(llmmag)+1,n_r_ic_maxmag*) [*complex,in*]
- **db_ic** (*ulmmag-(llmmag*)+1,*n_r_ic_maxmag*) [*complex*,*in*]
- **ddb_ic** (*ulmmag-(llmmag*)+1,*n_r_ic_maxmag*) [*complex*,*in*]
- aj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,in]
- **dj_ic** (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,in]
- **ddj_ic** (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,in]
- **l_frame** [logical,in]

Called from output ()

```
Call to dtb_from_rloc_to_lo(),
    dtb_gather_lo_on_rank0()
rbrspec(),
    rbpspec(),
```

10.17.4 dtB_arrays.f90

Needed modules

- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- precision_mod: This module controls the precision used in MagIC
- constants (zero ()): module containing constants and parameters used in the code.
- truncation (lmp_max_dtb()): This module defines the grid points and the truncation

Types

• type dtb_arrays_mod/unknown_type

Type fields

```
- % bpvtsn2lm(*)[complex,allocatable]
```

- % btvrlm(*)[complex,allocatable]
- % brvzlm(*)[complex,allocatable]
- % btvzlm(*) [complex,allocatable]
- % btvpcotlm(*)[complex,allocatable]
- % btvpsn2lm(*)[complex,allocatable]
- % btvzsn2lm(*)[complex,allocatable]
- % bpvtcotlm(*)[complex,allocatable]
- % bpvtlm(*)[complex,allocatable]
- % brvplm (*) [complex,allocatable]
- % bpvrlm(*)[complex,allocatable]
- % btvzcotlm(*)[complex,allocatable]
- % brvtlm(*) [complex,allocatable]
- % btvplm (*) [complex,allocatable]

Subroutines and functions

```
Parameters this [real]

subroutine dtb_arrays_mod/finalize(this)

Parameters this [real]

subroutine dtb_arrays_mod/set_zero(this)

Parameters this [real]

10.17.5 out_dtB_frame.f90
```

Quick access

```
Routines lm2pt(), get_dtb(), write_dtb_frame(), get_bpol(), get_btor()
```

- horizontal_data(dplm(), osn1(), dlh(), d_lp1(), dphi(), n_theta_cal2ord(), plm(), sintheta(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- movie_data (n_movie_fields_ic(), n_movie_field_type(), n_movie_surface(), movie_const(), n_movie_file(), n_movie_fields(), n_movie_const(), n_movie_type())
- fft: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5

- dtb_mod (pstrlm(), tdiflmic(), tadvlm(), tomelm(), tadvlmic(), tdiflm(), pdiflmic(), padvlm(), pdiflm(), padvlmic(), tstrlm()): This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output....
- precision_mod: This module controls the precision used in MagIC
- radial_der_even(get_drns_even())
- logic(l_cond_ic()): Module containing the logicals that control the run
- radial_der (get_dr()): Radial derivatives functions
- truncation: This module defines the grid points and the truncation
- blocking (lm2(), nthetabs(), sizethetab(), lm2m(), lm2l(), nfs()): Module containing blocking information
- constants (zero(), ci(), one()): module containing constants and parameters used in the code.
- radial_functions (rscheme_oc(), dr_fac_ic(), or1(), r_ic(), r(), chebt_ic_even(), r_icb(), chebt_ic()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Subroutines and functions

```
\textbf{subroutine} \hspace{0.1cm} \texttt{out\_dtb\_frame} / \textbf{write\_dtb\_frame} \hspace{0.1cm} (\textit{n\_movie}, \textit{b}, \textit{db}, \textit{aj}, \textit{dj}, \textit{b\_ic}, \textit{db\_ic}, \textit{aj\_ic}, \textit{dj\_ic})
```

Controls output of specific movie frames related to magnetic field production and diffusion.

Parameters

- **n_movie** [integer,in]
- **b** (lm_maxmag,n_r_maxmag) [complex,in]
- **db** (lm_maxmag,n_r_maxmag) [complex,in]
- aj (lm_maxmag,n_r_maxmag) [complex,in]
- **dj** (lm_maxmag,n_r_maxmag) [complex,in]
- **b_ic** (lm_maxmag,n_r_ic_maxmag) [complex,in]
- **db_ic** (lm_maxmag,n_r_ic_maxmag) [complex,in]
- aj_ic (lm_maxmag,n_r_ic_maxmag) [complex,in]
- **dj_ic** (lm_maxmag,n_r_ic_maxmag) [complex,in]

```
Called from write_movie_frame()
```

```
Call to get_dtb(), get_bpol(), get_btor(), lm2pt(), get_drns_even()
```

 $\begin{tabular}{ll} \textbf{subroutine} & \texttt{out_dtb_frame/get_dtb} (dtb, dtblm, dimb1, dimb2, n_r, n_theta_start, n_theta_block, \\ & l_ic) \end{tabular}$

- **dtb** (*) [real,out]
- **dtblm** (dimb1,dimb2) [complex,in]
- dimb1 [integer,in,]

- dimb2 [integer,in,]
- **n_r** [integer,in] :: No. of radial grid point
- n_theta_start [integer,in] :: No. of theta to start with
- n_theta_block [integer,in] :: Size of theta block
- 1 ic [logical,in] :: =true if inner core field

Called from write dtb frame()

Purpose of this subroutine is to calculate the components Br, Bt, and Bp of the poloidal magnetic field PolLM (l,m space) at the radial grid point r=rT and the block of theta grid points from n_theta=n_theta_start to n_theta=n_theta_start+n_theta_block-1 and for all phis. For IIC=.true. the inner core field is calculated, to get the IC field for a conducting inner core PolLM has to be the poloidal field at the ICB.

Parameters

- pollm (lm_max) [complex,in] :: field in (l,m)-space for rT
- **dpollm** (*lm_max*) [*complex,in*] :: dr field in (l,m)-space for rT
- **br** (*nrp*,*) [*real*,*out*]
- **bt** (*nrp*,*) [real,out]
- **bp** (*nrp*,*) [real,out]
- **rt** [real,in] :: radius
- **n_theta_start** [integer,in] :: first theta to be treated
- n_theta_block [integer,in] :: last theta
- **lic** [logical,in] :: true for inner core, special rDep!

 $\textbf{Called from} \ \textit{write_dtb_frame()}$

Call to fft_thetab()

subroutine out_dtb_frame/**get_btor**(tlm, bt, bp, rt, n_theta_start, n_theta_block, lic)

Purpose of this subroutine is to calculate the components Bt and Bp of the toroidal magnetic field Tlm (in l,m space) at the radial grid point r=rT and the block of theta grid points from n_theta=n_theta_start to n_theta=n_theta_start+n_theta_block-1 and for all phis. For lIC=.true. the inner core field is calculated, to get the IC field for a conducting inner core Plm has to be the toroidal field at the ICB.

- tlm (lm_max) [complex,in] :: field in (l,m)-space for rT
- **bt** (*nrp*,*) [real,out]
- **bp** (*nrp*,*) [real,out]
- rt [real,in] :: radius
- **n theta start** [integer, in] :: first theta to be treated
- n_theta_block [integer,in] :: last theta

• **lic** [logical,in] :: true for inner core, special rDep!

```
Called from write_dtb_frame()
Call to fft_thetab()
```

```
subroutine out_dtb_frame/lm2pt (alm, aij, rt, nthetastart, lic, lrcomp)
```

Spherical harmonic transform from alm(l,m) to aij(phi,theta) Radial field components are calculated for lrComp=.true. Done within the range [n_theta_min,n_theta_min+n_theta_block-1] Used only for graphic output.

Parameters

- alm (*) [complex,in] :: field in (l,m)-space
- aij (nrp,*) [real,out] :: field in (theta,phi)-space
- **rt** [real,in]
- **nthetastart** [integer,in] :: first theta to be treated
- **lic** [logical,in] :: true for inner core, extra factor!
- **Ircomp** [logical,in] :: true for radial field components

```
Called from write_dtb_frame()
Call to fft_thetab()
```

10.17.6 TO. £90

Description

This module contains information for TO calculation and output

Quick access

```
Variables bpsdas_rloc, bpzas_rloc, bpzdas_rloc, bs2as_rloc, bspas_rloc, bspdas_rloc, bszas_rloc, bzpdas_rloc, ddzasl, dzastrlmr, dzastrlmr_rloc, dzcorlmr, dzcorlmr_rloc, dzddvplmr, dzddvplmr_rloc, dzdvplmr, dzdvplmr_rloc, dzlflmr, dzlflmr_rloc, dzrstrlmr, dzrstrlmr_rloc, dzstrlmr, dzstrlmr_rloc, v2as_rloc
```

 $\textbf{Routines} \ \textit{initialize_to()}, \textit{finalize_to()}, \textit{gettofinish()}, \textit{getto()}, \textit{gettonext()}$

- horizontal_data(dthetala(), dlh(), hdif_v(), dthetals(), sintheta(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- lmloop_data(llmmag(), ulmmag())

- radial_data (n_r_cmb(), nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- precision_mod: This module controls the precision used in MagIC
- legendre_grid_to_spec(legtfas2())
- logic (l_mag(), lverbose()): Module containing the logicals that control the run
- physical_parameters (kbotv(), ktopv(), corfac()): Module containing the physical parameters
- truncation (n_r_maxstr(), l_max(), nrp(), n_phi_maxstr(), n_theta_maxstr()): This module defines the grid points and the truncation
- blocking (1m2(), nfs()): Module containing blocking information
- constants (two (), one ()): module containing constants and parameters used in the code.
- radial_functions (orho1(), or4(), or2(), or3(), or1(), beta(), r(), dbeta()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

- torsional_oscillations/dzlflmr_rloc(:,:) [real,allocatable/public]
- torsional_oscillations/dzddvplmr(:,:) [real,allocatable/public]
- torsional oscillations/dzastrlmr rloc(:,:) [real,allocatable/public]
- torsional_oscillations/dzlflmr(:,:) [real,allocatable/public]
- torsional_oscillations/dzrstrlmr_rloc(:,:) [real,allocatable/public]
- torsional_oscillations/v2as_rloc(:,:) [real,allocatable/public]
- torsional_oscillations/dzcorlmr(:,:) [real,allocatable/public]
- torsional_oscillations/dzdvplmr(:,:) [real,allocatable/public]
- torsional_oscillations/bs2as_rloc(:,:) [real,allocatable/public]
- torsional_oscillations/dzrstrlmr(:,:) [real,allocatable/public]
- torsional_oscillations/ddzasl(:,:) [real,allocatable/public]
- torsional_oscillations/bspas_rloc(:,:) [real,allocatable/public]
- torsional_oscillations/bspdas_rloc(:,:) [real,allocatable/public]
- torsional oscillations/dzdvplmr rloc(:,:) [real,allocatable/public]
- torsional_oscillations/dzstrlmr(:,:) [real,allocatable/public]
- torsional_oscillations/bpzas_rloc(:,:) [real,allocatable/public]
- torsional_oscillations/dzstrlmr_rloc(:,:) [real,allocatable/public]
- torsional_oscillations/dzcorlmr_rloc(:,:) [real,allocatable/public]
- torsional_oscillations/bzpdas_rloc(:,:) [real,allocatable/public]
- torsional_oscillations/bpsdas_rloc(:,:) [real,allocatable/public]
- torsional_oscillations/dzddvplmr_rloc(:,:) [real,allocatable/public]
- torsional_oscillations/bpzdas_rloc(:,:) [real,allocatable/public]
- torsional_oscillations/dzastrlmr(:,:) [real,allocatable/public]

• torsional_oscillations/bszas_rloc(:,:) [real,allocatable/public]

Subroutines and functions

```
subroutine torsional oscillations/initialize to()
    Allocate the memory needed
        Called from magic
subroutine torsional_oscillations/finalize_to()
    Deallocate the memory
```

Called from magic

subroutine torsional_oscillations/**getto**(vr, vt, vp, cvr, dvpdr, br, bt, bp, cbr, cbt, bslast, bplast, bzlast, dzrstrlm, dzastrlm, dzcorlm, dzlflm, dtlast, nr, nthetastart, nthetablocksize)

> This program calculates various axisymmetric linear and nonlinear variables for a radial grid point nR and a theta-block. Input are the fields vr,vt,vp,cvr,dvpdr Output are linear azimuthally averaged field VpAS (flow phi component), VpAS2 (square of flow phi component), V2AS (V*V), and Coriolis force Cor. These are give in (r,theta)-space. Also in (r,theta)-space are azimuthally averaged correlations of non-axisymmetric flow components and the respective squares: Vsp=Vs*Vp,Vzp,Vsz,VspC,VzpC,VszC. These are used to calulcate the respective correlations and Reynolds stress. In addition three output field are given in (lm,r) space: dzRstrLMr.dzAstrLMr.dzCorLM.dzLFLM.

> These are used to calculate the total Reynolds stress, advection and viscous stress later. Their calculation retraces the calculations done in the time-stepping part of the code.

- **vr** (*nrp*,*nfs*) [*real*,*in*]
- vt (nrp,nfs) [real,in]
- **vp** (*nrp*,*nfs*) [real,in]
- **cvr** (*nrp*,*nfs*) [real,in]
- **dvpdr** (*nrp*,*nfs*) [real,in]
- **br** (*nrp*,*nfs*) [real,in]
- **bt** (*nrp*,*nfs*) [real,in]
- **bp** (*nrp*,*nfs*) [*real*,*in*]
- **cbr** (*nrp*,*nfs*) [real,in]
- cbt (nrp,nfs) [real,in]
- **bslast** (*n_phi_maxstr*,*n_theta_maxstr*,*nrstop-*(*nrstart*)+1) [real,in]
- **bplast** (*n_phi_maxstr*,*n_theta_maxstr*,*nrstop-*(*nrstart*)+1) [*real*,*in*]
- **bzlast** (*n_phi_maxstr*,*n_theta_maxstr*,*nrstop-*(*nrstart*)+1) [real,in]
- **dzrstrlm** (*l_max*+2) [real,out]
- **dzastrlm** (*l_max*+2) [real,out]
- **dzcorlm** (*l_max*+2) [real,out]
- **dzlflm** (*l_max*+2) [real,out]

- **dtlast** [real,in] :: last time step
- **nr** [integer,in] :: radial grid point
- **nthetastart** [integer,in] :: theta block
- nthetablocksize [integer,in]

Call to legtfas2()

Preparing TO calculation by storing flow and magnetic field contribution to build time derivative.

Parameters

- **zas** (*l_max*+1) [real,in]
- **br** (*nrp*,*nfs*) [real,in]
- **bt** (*nrp*,*nfs*) [real,in]
- **bp** (*nrp*,*nfs*) [real,in]
- **ltonext** [logical,in]
- ltonext2 [logical,in]
- **dt** [real,in]
- dtlast [real,in]
- **nr** [integer,in]
- nthetastart [integer,in]
- **nthetablocksize** [integer,in]
- **bslast** (*n_phi_maxstr*,*n_theta_maxstr*,*nrstop-*(*nrstart*)+1) [real,out]
- **bplast** (*n_phi_maxstr*,*n_theta_maxstr*,*nrstop-*(*nrstart*)+1) [*real*,*out*]
- **bzlast** (*n phi maxstr*, *n theta maxstr*, *nrstop*-(*nrstart*)+1) [real, out]

> This program was previously part of getTO(...) It has now been separated to get it out of the thetablock loop.

- **nr** [integer,in]
- dtlast [real,in]
- **zas** (*l max*+1) [real,in]
- **dzas** (*l max*+1) [real,in]

```
• ddzas (l_max+1) [real,in]
```

- dzrstrlm (l_max+2) [real,in]
- **dzastrlm** (*l_max*+2) [real,in]
- **dzcorlm** (*l_max*+2) [real,in]
- **dzlflm** (*l* max+2) [real,in]

Called from do_iteration_thetablocking_openmp(), do_iteration_thetablocking_seq(),
 do_iteration_thetablocking_shtns()

10.17.7 TO_helpers.f90

Description

This module contains several helpful subroutines used in the TO calculations

Quick access

```
Routines getpastr(), getastr(), get_pas()
```

Needed modules

- precision_mod: This module controls the precision used in MagIC
- horizontal_data(dplm(), osn1()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- blocking (1m2 ()): Module containing blocking information
- constants (half(), two(), one()): module containing constants and parameters used in the code.
- truncation (1_max()): This module defines the grid points and the truncation

Variables

Subroutines and functions

Calculates axisymmetric phi component for a given toroidal potential flmn in spherical harmonic/Cheb space. This is calculated at radii rZ(nZmax) and matching colatitutes theta(nZmax) for which dPlm(theta) and OsinTS(theta) are provided for the south hemisphere. Points in the northern hemipshere use Plm symmetries.

- **fz** (*) [real,out]
- flmn (lmax + 1,*) [real,in]
- nzmax [integer,in]
- nzmaxa [integer,in,]

```
• lmax [integer,in,]
```

- rmin [real,in]
- rmax [real,in]
- nchebmax [integer,in]
- rz (0.5 * nzmaxa + 1.0) [real, in]
- **dplm** (lmax + 1,0.5 * nzmaxa + 1.0) [real,in]
- osints (0.5 * nzmaxa + 1.0) [real,in]

Called from outto(), outpv()

subroutine to_helpers/get_pas(tlm, bp, rt, nthetastart, sizethetablock)

Purpose of this subroutine is to calculate the axisymmetric phi component Bp of an axisymmetric toroidal field Tlm given in spherical harmonic space (1,m=0).

Parameters

- tlm (*) [real,in] :: field in (l,m)-space for rT
- **bp** (*) [real,out]
- rt [real,in] :: radius
- **nthetastart** [integer,in] :: first theta to be treated
- **sizethetablock** [integer,in] :: size of theta block

Called from outto()

subroutine to_helpers/**getastr**(fz, flmn, nzmax, nzmaxa, lmax, rmin, rmax, nchebmax, rz, plm)

Calculates function value at radii rZ(nZmax) and colatitudes for which Plm(theta) is given from the spherical harmonic/Chebychev coefficients of an axisymmetric function (order=0).

Parameters

- **fz** (*) [real,out]
- flmn (lmax + 1,*) [real,in]
- nzmax [integer,in]
- nzmaxa [integer,in,]
- lmax [integer,in,]
- rmin [real,in]
- rmax [real,in]
- nchebmax [integer,in]
- rz (0.5 * nzmaxa + 1.0) [real, in]
- plm (lmax + 1,0.5 * nzmaxa + 1.0) [real,in]

Called from outto()

10.17.8 TO arrays.f90

Needed modules

- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- precision_mod: This module controls the precision used in MagIC
- truncation (1_max()): This module defines the grid points and the truncation

Types

```
• type to_arrays_mod/unknown_type
```

Type fields

- % dzcorlm(*)[real,allocatable]
- % dzlflm(*)[real,allocatable]
- % dzrstrlm(*)[real,allocatable]
- % dzastrlm(*)[real,allocatable]

Subroutines and functions

```
Parameters this [real]
subroutine to_arrays_mod/finalize(this)
Parameters this [real]
subroutine to_arrays_mod/set_zero(this)
```

Parameters this [real]

10.17.9 out TO.f90

Quick access

Variables ns_on_last_rank, ns_per_rank, nsmax, nsstart, nsstop, ntozfile, nzmaxa, movfile, tofilenhs, tofileshs, tayfile, timeave, timelast, nzmaxs, nzmaxs_sloc, chebt_z, bpsdlmr, bpsdlmr_rloc, bpzdlmr, bpzdlmr_rloc, bsplmr, bpzlmr_rloc, bs2lmr, bs2lmr_rloc, bspdlmr, bspdlmr_rloc, bsplmr, bsplmr_rloc, bszlmr, bszlmr_rloc, bzpdlmr, bzpdlmr_rloc, dzvplmr, dzvplmr_loc, osints, rz, v2lmr, v2lmr_rloc, zz, zz_sloc, astrm, astrm_sloc, clm, clm_sloc, corm, corm_sloc, dvpm, dvpm_sloc, lfm, lfm_sloc, rstrm, rstrm_sloc, strm, strm_sloc, vpm, vpm_sloc, dplms, plms

- horizontal_data (phi (), gauss (), theta_ord (), sintheta ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- chebint_mod(chebint(), chebintinit())
- useful (abortrun (), logwrite ()): library with several useful subroutines
- lmloop_data(llm(), ulm())
- to_helpers (getpastr(), get_pas(), getastr()): This module contains several helpful subroutines used in the TO calculations
- legendre_grid_to_spec(legtfas2(), legtfas())
- cosine transform odd
- integration (rint_r()): Radial integration functions
- parallel_mod: This module contains the blocking information
- num_param(tscale()): Module containing numerical and control parameters
- physical_parameters(pr(), prmag(), lffac(), ek(), radratio(), ra()): Module containing the physical parameters
- radial_functions (r_icb(), r_cmb(), rscheme_oc(), r(), orho1()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- precision_mod: This module controls the precision used in MagIC
- plms_theta(plm_theta())
- blocking (lo_map(), nthetabs(), nfs(), sizethetab()): Module containing blocking information
- constants (two(), one(), four(), half(), vol_oc(), pi()): module containing constants and parameters used in the code.
- truncation (l_max(), n_r_maxstr(), minc(), n_phi_max(), lstressmem(), n_r_max(), n_theta_maxstr(), lm_max(), n_theta_max()): This module defines the grid points and the truncation
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- output_data(n_log_file(), zdens(), tag(), runid(), log_file(), sdens()): This module contains the parameters for output control
- torsional_oscillations (dzastrlmr(), dzastrlmr_rloc(), dzrstrlmr(), v2as_rloc(), dzdvplmr(), bspdas_rloc(), bpzas_rloc(), dzstrlmr_rloc(), dzcorlmr_rloc(), dzlflmr_rloc(), dzddvplmr_rloc(), bzpdas_rloc(), dzddvplmr(), dzlflmr(), dzcorlmr(), bs2as_rloc(), dzrstrlmr_rloc(), bspas_rloc(), dzdvplmr_rloc(), dzstrlmr(), bpsdas_rloc(), bpzdas_rloc(), bszas_rloc(): This module contains information for TO calculation and output
- radial_data (nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- logic (l_save_out (), lverbose ()): Module containing the logicals that control the run

Variables

- outto_mod/dzvplmr_loc(:,:) [real,private/allocatable]
- outto_mod/rstrm_sloc(:,:) [real,private/allocatable]
- outto_mod/tayfile [character,private]
- outto_mod/chebt_z (:) [costf_odd_t,private/allocatable]
- outto_mod/lfm(:,:) [real,private/allocatable]
- outto_mod/nzmaxa [integer,private]
- outto_mod/bpzlmr (:,:) [real,private/allocatable]
- outto_mod/osints(:,:) [real,private/allocatable]
- outto_mod/nzmaxs_sloc(:) [integer,private/allocatable]
- outto_mod/ns_on_last_rank [integer,private]
- outto_mod/astrm_sloc(:,:) [real,private/allocatable]
- outto_mod/bsplmr_rloc(:,:) [real,private/allocatable]
- outto_mod/ns_per_rank [integer,private]
- outto_mod/zz(:,:) [real,private/allocatable]
- outto_mod/bpsdlmr (:,:) [real,private/allocatable]
- outto_mod/nzmaxs(:)[integer,private/allocatable]
- outto_mod/v2lmr(:,:) [real,private/allocatable]
- outto_mod/v2lmr_rloc(:,:) [real,private/allocatable]
- outto_mod/clm(:,:) [real,private/allocatable]
- outto_mod/clm_sloc(:,:) [real,private/allocatable]
- outto_mod/timelast [real,private] ,tNorm
- outto_mod/nsstop [integer,private]
- outto_mod/bpzdlmr (:,:) [real,private/allocatable]
- outto_mod/bspdlmr (:,:) [real,private/allocatable]
- outto_mod/rz(:,:) [real,private/allocatable]
- outto_mod/bszlmr_rloc(:,:) [real,private/allocatable]
- outto_mod/lfm_sloc(:,:) [real,private/allocatable]
- outto_mod/**timeave** [real,private]
- outto_mod/**dplms** (:,:,:) [real,private/allocatable]
- outto_mod/plms (:,:,:) [real,private/allocatable]
- outto_mod/bsplmr(:,:) [real,private/allocatable]
- outto_mod/zz_sloc(:,:) [real,private/allocatable]
- outto_mod/rstrm(:,:) [real,private/allocatable]
- outto_mod/movfile [character,private]

- outto_mod/corm (:,:) [real,private/allocatable]
- outto_mod/dzvplmr (:,:) [real,private/allocatable]
- outto_mod/bs21mr (:,:) [real,private/allocatable]
- outto_mod/astrm(:,:) [real,private/allocatable]
- outto_mod/strm_sloc(:,:) [real,private/allocatable]
- outto_mod/bpzdlmr_rloc (:,:) [real,private/allocatable]
- outto_mod/bspdlmr_rloc(:,:) [real,private/allocatable]
- outto_mod/**vpm**(:,:) [real,private/allocatable]
- outto_mod/nsmax [integer,private]
- outto_mod/bs2lmr_rloc(:,:) [real,private/allocatable]
- outto_mod/dvpm_sloc(:,:) [real,private/allocatable]
- outto_mod/corm_sloc(:,:) [real,private/allocatable]
- outto_mod/ntozfile [integer,private]
- outto_mod/bzpdlmr_rloc(:,:) [real,private/allocatable]
- outto_mod/**vpm_sloc** (:,:) [real,private/allocatable]
- outto_mod/bzpdlmr (:,:) [real,private/allocatable]
- outto_mod/bpzlmr_rloc(:,:) [real,private/allocatable]
- outto_mod/tofilenhs [character,private]
- outto_mod/dvpm (:,:) [real,private/allocatable]
- outto_mod/strm(:,:) [real,private/allocatable]
- outto_mod/bszlmr(:,:) [real,private/allocatable]
- outto_mod/nsstart [integer,private]
- outto_mod/tofileshs[character,private]
- outto_mod/bpsdlmr_rloc(:,:) [real,private/allocatable]

Subroutines and functions

subroutine outto_mod/outto (time, n_time_step, ekin, ekintas, ntosets, ntomovsets, ntormssets, lto-mov, ltorms, ltozwrite, z, omega_ic, omega_ma)

Output of axisymmetric zonal flow, its relative strength, its time variation, and all forces acting on it. The slowest part in the TO process is the repetitious calculation of plms by subroutine plm_theta. They are needed in getAStr and getPAStr when I transform on the cylindrical grid. The necessary plms could simply be calculated one and then be stored for later use!

Parameters

```
• time [real,in]
```

- n_time_step [integer,in]
- ekin [real,in]
- ekintas [real,in]
- **ntosets** [integer,inout]
- **ntomovsets** [integer,inout]
- **ntormssets** [integer,inout]
- **Itomov** [logical,in]
- **Itorms** [logical,inout]
- **ltozwrite** [logical,inout]
- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- omega_ic [real,in]
- omega_ma [real,in]

Called from output ()

```
Call to legtfas(), legtfas2(), outto_allgather_rloc(), chebintinit(),
    plm_theta(), getpastr(), getastr(), chebint(), abortrun(), logwrite(),
    get_pas(), rint_r()
```

subroutine outto_mod/outto_allgather_rloc()

MPI communicators for TO outputs

Called from outto()

10.17.10 radial_spectra.f90

Quick access

```
Variables filehandle
```

Routines rbrspec(), rbpspec()

- horizontal_data(dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel_mod: This module contains the blocking information
- useful (cc2real ()): library with several useful subroutines
- output_data(tag()): This module contains the parameters for output control
- logic(l_cond_ic()): Module containing the logicals that control the run
- lmloop_data(llm(), ulm())
- radial_data (n_r_icb()): This module defines the MPI decomposition in the radial direction.

- precision_mod: This module controls the precision used in MagIC
- num_param (escale()): Module containing numerical and control parameters
- truncation(lm_max(), n_r_ic_max(), l_max(), n_r_tot(), n_r_max()): This module defines the grid points and the truncation
- lmmapping (mappings())
- blocking (st_map()): Module containing blocking information
- constants (four(), half(), pi(), one()): module containing constants and parameters used in the code.
- radial_functions (r_icb(), r_ic(), or2()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

• radial_spectra/filehandle [integer, private]

Subroutines and functions

subroutine radial_spectra/rbrspec(time, pol, polic, fileroot, lic, map)

Parameters

- time [real,in]
- **pol** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **polic** (*ulm*-(*llm*)+1,*n*_*r*_*ic*_*max*) [*complex*,*in*]
- **fileroot** [character,in]
- lic [logical,in]
- map [mappings,in]

Called from get_dtblmfinish(), output()

Call to cc2real()

subroutine radial_spectra/rbpspec(time, tor, toric, fileroot, lic, map)

Called from rank0, map gives the lm order of Tor and TorIC

Parameters

- time [real,in]
- **tor** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **toric** (*ulm*-(*llm*)+1,*n_r_ic_max*) [*complex*,*in*]
- **fileroot** [character,in]
- lic [logical,in]
- map [mappings,in]

Called from get_dtblmfinish(), output()

Call to cc2real()

10.17.11 outGeos.f90

Description

This module is used to calculate the outputs when either l_par or l_PV are set to .true.

Quick access

```
Variables n_geos_file, geos_file, timeold, nzc, nzc_sloc, nz2, eps, ddws_global,
    dws_global, dzs_global, osintspv, rzpv, ws_global, zs_global, dplmspv,
    dplmz, plmspv, plmz, vorold
Routines initialize_geos_mod(), finalize_geos_mod(), outpv(), getegeos(),
    costf_arrays(), getdvptr()
```

- horizontal_data (dphi (), phi (), dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel_mod: This module contains the blocking information
- cosine_transform_odd(costf_odd_t())
- fft (fft_to_real()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- mem_alloc (bytes_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- chebint_mod
- output_data(zdens(), tag(), runid(), sdens()): This module contains the parameters for output control
- logic (l_corrmov(), l_sric(), l_save_out(), lverbose(), l_anel()): Module containing the logicals that control the run
- lmloop_data(llm(), ulm())
- to_helpers (getpastr()): This module contains several helpful subroutines used in the TO calculations
- precision_mod: This module controls the precision used in MagIC
- communications (gather_all_from_lo_to_rank0(), gt_oc())
- plms_theta(plm_theta())
- num_param(tscale()): Module containing numerical and control parameters
- physical_parameters(pr(), prmag(), radratio(), ra(), ek()): Module containing the physical parameters
- truncation (l_max(), minc(), n_phi_max(), l_axi(), n_r_max(), n_m_max(), m_max(), lm_max(), nrp()): This module defines the grid points and the truncation
- blocking (st_map(), lm2m(), lm2l(), lm2mc(), lo_map()): Module containing blocking information

- constants (ci(), two(), one(), zero(), half(), pi()): module containing constants and parameters used in the code.
- radial_functions (r_icb(), r_cmb(), rscheme_oc(), orho1()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

- geos_mod/chebt_z (:) [costf_odd_t,private/allocatable]
- geos_mod/nzmaxa [integer,private]
- geos_mod/ws_global (:,:) [complex,private/allocatable]
- geos_mod/osintspv(:,:) [real,private/allocatable]
- geos_mod/zz(:,:) [real,private/allocatable]
- geos_mod/ns_per_rank [integer,private]
- geos_mod/nzmaxs(:)[integer,private/allocatable]
- geos_mod/nz2 (:,:) [integer,private/allocatable]
- geos_mod/nsstop[integer,private]
- geos_mod/nzc_sloc(:) [integer,private/allocatable]
- geos_mod/rzpv(:,:) [real,private/allocatable]
- geos_mod/**dplmz** (:,:,:) [real,private/allocatable]
- geos_mod/dzs_global (:,:) [complex,private/allocatable]
- geos_mod/plmz (:,:,:) [real,private/allocatable]
- geos_mod/**dplms** (:,:,:) [real,private/allocatable]
- geos_mod/plms (:,:,:) [real,private/allocatable]
- geos_mod/**dplmspv** (:,:,:) [real,private/allocatable]
- geos_mod/n_geos_file [integer,private]
- geos_mod/timeold[real,private]
- geos_mod/nsstart [integer,private]
- geos_mod/ddws_global (:,:) [complex,private/allocatable]
- geos mod/ns on last rank[integer,private]
- geos_mod/nsmax [integer,private]
- geos_mod/osints(:,:) [real,private/allocatable]
- geos_mod/zs_global(:,:) [complex,private/allocatable]
- geos_mod/eps [real,private/parameter=10.0_cp*epsilon(one)]
- geos_mod/nzc(:) [integer, private/allocatable]
- geos_mod/geos_file [character,private]
- geos_mod/**vorold**(:,:,:) [real,private/allocatable]
- geos_mod/plmspv (:,:,:) [real,private/allocatable]

- geos_mod/dws_global (:,:) [complex,private/allocatable]
- geos_mod/rz(:,:) [real,private/allocatable]

Subroutines and functions

```
subroutine geos_mod/initialize_geos_mod(l_geos, l_pv)
```

Memory allocation in Egeos

Parameters

- l_geos [logical,in]
- l_pv [logical,in]

Called from magic

```
subroutine geos_mod/finalize_geos_mod(l_geos, l_pv)
```

Memory deallocation

Parameters

- l_geos [logical,in]
- 1 pv [logical,in]

Called from magic

```
subroutine geos_mod/getegeos (time, ngeossets, w, dw, ddw, z, dz, geos, dpflow, dzflow)
```

Output of axisymmetric zonal flow, its relative strength, its time variation, and all forces acting on it. The slowest part in the TO process is the repitions calculation of Plms by subroutine plm_theta. They are needed in getDVptr when I transform on the cylindrical grid. The necessary plms could simply be calculated one and then be stored for later use! See s_outTOnew.f.

- time [real,in]
- **ngeossets** [integer,in]
- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- \mathbf{dw} (ulm-(llm)+1,n_r_max) [complex,in]
- **ddw** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- \mathbf{z} (ulm-(llm)+1,n_r_max) [complex,in]
- **dz** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **geos** [real,out] :: Degree of geostrophy
- **dpflow** [real,out] :: RMS lengths scale
- **dzflow** [real,out] :: RMS lengths scale

```
Called from output ()
```

subroutine geos_mod/outpv (time, l_stop_time, npvsets, w, dw, ddw, z, dz, omega_ic, omega_ma)

Output of z-integrated axisymmetric rotation rate Vp/s and s derivatives

Parameters

- time [real,in]
- l_stop_time [logical,in]
- **npvsets** [integer,inout]
- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **dw** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **ddw** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **dz** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- omega_ic [real,in]
- omega_ma [real,in]

Called from output ()

Call to costf_arrays(), plm_theta(), getpastr(), getdvptr()

subroutine geos_mod/**getdvptr**(w, dw, ddw, z, dz, rmin, rmax, rs, nzmax, nzmaxa, plms, dplms, osints, kindcalc, vrs, vts, vps, vors[, dpek])

This subroutine calculates the three flow components VrS,VtS,VpS at a (r,theta,all phis) and (t,pi=theta, all phis). Here r=rS, PlmS=Plm(theta), dPlmS=sin(theta)*dTheta Plm(theta), and OsinTS=1/sin(theta). The flow is calculated for all n_phi_max azimuthal points used in the code, and for corresponding latitudes north and south of the equator. When kindCalc=1, the subroutine also calculates dpEk and dzEk which are phi averages of (d Vr/d phi)**2 + (d Vtheta/d phi)**2 + (d Vphi/d phi)**2 and (d Vr/d z)**2 + (d Vtheta/d z)**2 + (d Vphi/d z)**2, respectively.

Note: on input wS=w/r^2, dwS=dw/r, ddwS=ddw/r, zS=z/r

- w (lm_max,n_r_max) [complex,in]
- **dw** (*lm_max*,*n_r_max*) [*complex*,*in*]
- **ddw** (lm_max,n_r_max) [complex,in]
- **z** (lm_max,n_r_max) [complex,in]
- **dz** (*lm_max*,*n_r_max*) [*complex*,*in*]
- **rmin** [real,in] :: radial bounds
- rmax [real,in]
- **rs** (nzmaxa) [real,in]
- nzmax [integer,in] :: number of (r,theta) points
- nzmaxa [integer,in,]
- **plms** (*lm_max*,0.5 * *nzmaxa* + 1.0) [*real,in*]

```
• dplms (lm_max, 0.5 * nzmaxa + 1.0) [real, in]
      • osints (0.5 * nzmaxa + 1.0) [real,in]
      • kindcalc [integer,in]
      • vrs (nrp,nzmaxa) [real,out]
      • vts (nrp,nzmaxa) [real,out]
      • vps (nrp,nzmaxa) [real,out]
      • vors (nrp,nzmaxa) [real,out]
Options dpek (nzmaxa) [real,out,optional]
```

```
Called from outpv(), getegeos()
Call to fft_to_real()
```

```
subroutine geos_mod/costf_arrays (w, dw, ddw, z, dz)
```

This subroutine performs local copy of LM-distributed arrays, do a cosine transform and then allgather them

Parameters

```
• w (ulm-(llm)+1,n_r_max) [complex,in]
```

- dw (ulm-(llm)+1,n r max) [complex,in]
- \mathbf{ddw} (ulm-(llm)+1,n r max) [complex,in]
- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- dz (ulm-(llm)+1,n_r_max) [complex,in]

```
Called from outpv(), getegeos()
```

Call to gather_all_from_lo_to_rank0()

10.17.12 chebInt.f90

Quick access

```
Routines chebintinit(), chebintd(), chebint()
```

- parallel mod: This module contains the blocking information
- cosine_transform_odd
- useful (abortrun ()): library with several useful subroutines
- precision_mod: This module controls the precision used in MagIC
- radial_der (get_dcheb ()): Radial derivatives functions
- chebyshev_polynoms_mod(cheb_grid())
- constants (four (), two (), half ()): module containing constants and parameters used in the code.

Variables

Subroutines and functions

Parameters

- **zmin** [real,in] :: integration interval!
- zmax [real,in]
- **znorm** [real,in] :: norm interval length
- nnorm [integer,in] :: suggested number of grid points for norm length
- ngridpointsmax [integer,in] :: dimension of z on input
- **z** (ngridpointsmax) [real,out] :: grid points, dimension at >= nGridPointsMax
- **ngridpoints** [integer,out] :: number of used grid points
- **chebt** [costf_odd_t,out]

```
Called from outto(), getegeos()
```

Call to abortrun(), cheb_grid()

function chebint_mod/chebint (f, zmin, zmax, ngridpoints, ngridpointsmax, chebt)

Parameters

- f (ngridpointsmax) [real,in] :: function on grid points
- **zmin** [real,in] :: integration boundaries
- zmax [real,in]
- **ngridpoints** [integer,in] :: No of grid points
- ngridpointsmax [integer,in,] :: No of max grid points
- **chebt** [costf_odd_t,in]

Return chebint [real]

Called from outto(), getegeos()

function chebint_mod/**chebintd**(*f, lderiv, zmin, zmax, ngridpoints, ngridpointsmax, chebt*)

Parameters

- **f** (ngridpointsmax) [real,inout] :: function on grid points
- **Ideriv** [logical,in]
- **zmin** [real,in] :: integration boundaries
- **zmax** [real,in]
- **ngridpoints** [integer,in] :: No of grid points
- ngridpointsmax [integer,in,] :: No of max grid points
- **chebt** [costf_odd_t,in]

Return chebintd [real]

Called from getegeos ()

10.17.13 outOmega.f90

Description

This module allows to compute the axisymmetric zonal flow versus the cylindrical radius s. By

Quick access

```
Routines outomega(), lnpas2tr()
```

Needed modules

- parallel_mod: This module contains the blocking information
- cosine_transform_odd
- useful (abortrun ()): library with several useful subroutines
- output_data(tag()): This module contains the parameters for output control
- lmloop_data(llm(), ulm())
- precision_mod: This module controls the precision used in MagIC
- plms_theta(plm_theta())
- logic (lverbose ()): Module containing the logicals that control the run
- truncation (lm_max(), l_max(), minc(), n_r_max()): This module defines the grid points and the truncation
- blocking (lo_map()): Module containing blocking information
- constants (half(), two(), one()): module containing constants and parameters used in the code.
- radial_functions (r_cmb(), r_icb(), rscheme_oc(), orho1()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

• omega/nsmax [integer,private/parameter=300] Number of cylindrical radial grid points

Subroutines and functions

```
subroutine omega/outomega(z, omega_ic)
```

Output of axisymmetric zonal flow omega(s) into field omega. TAG, where s is the cylindrical radius. This is done for the southern and norther hemispheres at $z=+-(r_icb+0.5)$

Parameters

• **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]

```
    omega_ic [real,in]
    Called from output()
```

Call to lnpas2tr()

function omega/lnpas2tr(f, lmmax, a, b, lmax, minc, nchebmax, theta, r)

Parameters

- **f** (lmmax,*) [real,in]
- **lmmax** [integer,in,]
- **a** [real,in]
- **b** [real,in]
- lmax [integer,in]
- minc [integer,in]
- nchebmax [integer,in]
- theta [real,in]
- **r** [real,in]

Return Inpas2tr [real]

Called from outomega()

Call to plm_theta(), abortrun()

10.17.14 nl_special_calc.f90

Description

This module allows to calculcate several diagnostics that need to be computed in the physical space (non-linear quantities)

Quick access

```
Routines get_visc_heat(), get_helicity(), get_fluxes(), get_perppar(),
    get_nlblayers()
```

- horizontal_data(cosn2(), osn2(), o_sin_theta_e2(), sn2(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- legendre_grid_to_spec(legtfas2(), legtfas())
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- precision_mod: This module controls the precision used in MagIC
- logic(l_tp_form(), l_anelastic_liquid(), l_mag_nl()): Module containing the logicals that control the run

- physical_parameters (vischeatfac(), thexpnb(), ek()): Module containing the physical parameters
- radial_functions (alpha0(), orho1(), orho2(), or4(), or2(), or1(), visc(), beta(), temp0(), r()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (nfs(), sizethetab()): Module containing blocking information
- constants (half(), pi(), two(), third(), one()): module containing constants and parameters used in the code.
- truncation(1_maxmag(), 1_max(), nrp(), n_phi_max()): This module defines the grid points and the truncation

Variables

Subroutines and functions

Calculates axisymmetric contributions of:

- the horizontal velocity $u_h = \sqrt{u_\theta^2 + u_\phi^2}$
- its radial derivative $|\partial u_h/\partial r|$
- The thermal dissipation rate $(\nabla T)^2$

This subroutine is used when one wants to evaluate viscous and thermal dissipation layers

Parameters

- **vt** (*nrp*,*nfs*) [*real*,*in*]
- **vp** (*nrp*,*nfs*) [*real*,*in*]
- **dvtdr** (*nrp*,*nfs*) [real,in]
- **dvpdr** (*nrp*,*nfs*) [real,in]
- **dsdr** (nrp,nfs) [real,in]
- **dsdt** (*nrp*,*nfs*) [real,in]
- **dsdp** (nrp,nfs) [real,in]
- **uhlmr** (*l_max*+1) [real,out]
- **duhlmr** (*l_max*+1) [*real,out*]
- gradslmr (l max+1) [real,out]
- **nr** [integer,in]
- **nthetastart** [integer,in]

Call to legtfas2(), legtfas()

subroutine nl_special_calc/**get_perppar**(*vr*, *vt*, *vp*, *eperplmr*, *eparlmr*, *eperpaxilmr*, *eparaxilmr*, *nr*, *nthetastart*)

Calculates the energies parallel and perpendicular to the rotation axis

- $E_{\perp} = 0.5(v_s^2 + v_{\phi}^2)$ with $v_s = v_r \sin \theta + v_{\theta} \cos \theta$
- $E_{\parallel} = 0.5v_z^2$ with $v_z = v_r \cos \theta v_{\theta} * \sin \theta$

Parameters

- **vr** (*nrp*,*nfs*) [real,in]
- **vt** (*nrp*,*nfs*) [real,in]
- **vp** (*nrp*,*nfs*) [real,in]
- **eperplmr** (*l_max*+1) [real,out]
- **eparlmr** (*l_max*+1) [real,out]
- **eperpaxilmr** (*l_max*+1) [real,out]
- **eparaxilmr** (*l_max*+1) [real,out]
- **nr** [integer,in]
- nthetastart [integer,in]

Call to legtfas2()

Calculates the fluxes:

- Convective flux: $F_c = \rho T(u_r s)$
- Kinetic flux: $F_k = 1/2 \rho u_r (u_r^2 + u_\theta^2 + u_\phi^2)$
- Viscous flux: $F_{=} (u \cdot S)_r$

If the run is magnetic, then this routine also computes:

- · Poynting flux
- resistive flux

- **vr** (*nrp*,*nfs*) [real,in]
- **vt** (nrp,nfs) [real,in]
- **vp** (*nrp*,*nfs*) [real,in]
- **dvrdr** (nrp,nfs) [real,in]
- **dvtdr** (nrp,nfs) [real,in]
- **dvpdr** (nrp,nfs) [real,in]
- **dvrdt** (nrp,nfs) [real,in]
- **dvrdp** (*nrp*,*nfs*) [real,in]

```
sr (nrp,nfs) [real,in]
pr (nrp,nfs) [real,in]
br (nrp,nfs) [real,in]
bt (nrp,nfs) [real,in]
```

• **bp** (*nrp*,*nfs*) [*real*,*in*]

• **cbt** (*nrp*,*nfs*) [real,in]

• cbp (nrp,nfs) [real,in]

• fconvlmr (l_max+1) [real,out]

• **fkinlmr** (*l_max*+1) [real,out]

• **fvisclmr** (*l_max*+1) [real,out]

• **fpoynlmr** (*l_maxmag+1*) [real,out]

• **freslmr** (*l_maxmag+1*) [real,out]

• **nr** [integer,in]

• nthetastart [integer,in]

Call to legtfas2(), legtfas()

Calculates axisymmetric contributions of helicity HelLMr and helicity**2 Hel2LMr in (l,m=0,r) space.

- **vr** (*nrp*,*nfs*) [real,in]
- **vt** (*nrp*,*nfs*) [real,in]
- **vp** (*nrp*,*nfs*) [*real*,*in*]
- cvr (nrp,nfs) [real,in]
- **dvrdt** (nrp,nfs) [real,in]
- **dvrdp** (nrp,nfs) [real,in]
- **dvtdr** (*nrp*,*nfs*) [real,in]
- **dvpdr** (*nrp*,*nfs*) [real,in]
- **hellmr** (*l_max*+1) [*real*, *out*]
- **hel2lmr** (*l_max*+1) [*real,out*]
- helnalmr (*l_max*+1) [real,out]
- helna2lmr (*l_max*+1) [real,out]
- **nr** [integer,in]
- nthetastart [integer,in]

Calculates axisymmetric contributions of the viscous heating

Parameters

- **vr** (*nrp*,*nfs*) [*real*,*in*]
- **vt** (*nrp*,*nfs*) [real,in]
- **vp** (*nrp*,*nfs*) [*real*,*in*]
- cvr (nrp,nfs) [real,in]
- **dvrdr** (nrp,nfs) [real,in]
- **dvrdt** (nrp,nfs) [real,in]
- **dvrdp** (*nrp*,*nfs*) [real,in]
- **dvtdr** (*nrp*,*nfs*) [real,in]
- **dvtdp** (*nrp*,*nfs*) [real,in]
- **dvpdr** (*nrp*,*nfs*) [real,in]
- **dvpdp** (*nrp*,*nfs*) [real,in]
- visclmr (l_max+1) [real,out]
- **nr** [integer,in]
- **nthetastart** [integer,in]

Call to legtfas()

10.17.15 probes.f90

Quick access

```
Variables n_out_probes, n_theta_usr, rad_rank, rad_usr, n_phi_probes, probe_file, theta_probe, r_probe
```

Routines finalize_probes(), initialize_probes(), probe_out()

- horizontal_data(theta(), o_sin_theta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision_mod: This module controls the precision used in MagIC
- output_data(tag()): This module contains the parameters for output control

- logic (l_save_out ()): Module containing the logicals that control the run
- radial_data(nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- parallel_mod (rank ()): This module contains the blocking information
- num_param(vscale()): Module containing numerical and control parameters
- truncation(nrp(), n_phi_max(), n_r_max()): This module defines the grid points and the truncation
- blocking (nthetabs(), nfs(), sizethetab()): Module containing blocking information
- constants (pi ()): module containing constants and parameters used in the code.
- radial_functions (orho1(), r_cmb(), or2(), or1(), r(), r_icb()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

Variables

- probe_mod/r_probe [real,public] probe locations, r_probe in terms of r_cmb and theta in degrees
- probe_mod/n_theta_usr [integer,private]
- probe_mod/rad_usr[integer,private]
- probe_mod/rad_rank [integer,private]
- probe_mod/n_out_probes [integer,private]
- probe_mod/n_phi_probes [integer,public] number of probes in phi symmetrically distributed
- probe_mod/probe_file [character,private]
- probe_mod/theta_probe [real,public]

Subroutines and functions

Parameters

- time [real,in]
- **n_r** [integer,in] :: radial grod point no.
- **vp** (*nrp*,*) [real,in]
- n_theta_start [integer,in] :: start theta no.
- n_theta_block_size [integer,in] :: size of theta block

10.18 Reading and storing check points (restart files)

10.18.1 readCheckPoints.f90

Description

This module contains the functions that can help reading and mapping of the restart files

Quick access

- chebyshev (type_cheb_odd())
- parallel_mod: This module contains the blocking information
- cosine_transform_odd(costf_odd_t())
- useful (polynomial_interpolation(), abortrun()): library with several useful subroutines
- init_fields (tshift_ma1(), tshift_ma2(), omegaosz_ic2(), omegaosz_ic1(), tomega_ma1(), tomega_ma2(), start_file(), scale_xi(), scale_b(), omega_ic1(), omega_ic2(), scale_s(), scale_v(), tipdipole(), tomega_ic2(), tomega_ic1(), omega_ma2(), omega_ma1(), tshift_ic2(), tshift_ic1(), inform(), omegaosz_ma1(), omegaosz_ma2()): This module is used to construct the initial solution.
- finite_differences (type_fd()): This module is used to calculate the radial grid when finite differences are requested
- radial_scheme (type_rscheme()): This is an abstract type that defines the radial scheme used in MagIC
- !mloop data(ulmmag(), llmmag(), llm(), ulm())
- radial_data(n_r_cmb(), n_r_icb()): This module defines the MPI decomposition in the radial direction.
- precision_mod: This module controls the precision used in MagIC
- communications (scatter_from_rank0_to_lo())
- logic (l_rot_ic(), l_ab1(), l_chemical_conv(), l_mag(), l_heat(), l_srma(), l_mag_lf(), l_rot_ma(), l_sric(), l_cond_ic()): Module containing the logicals that control the run
- physical_parameters (pr(), kbotv(), prmag(), ek(), sigma_ratio(), radratio(), ktopv(), ra(), sc(), raxi(): Module containing the physical parameters
- radial_functions (r(), rscheme_oc(), chebt_ic(), cheb_norm_ic()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (lmstartb(), nlmbs(), lm2m(), lm2l(), lmstopb(), lo_map()): Module containing blocking information
- constants (one ()): module containing constants and parameters used in the code.

truncation(n_r_ic_max(), lm_maxmag(), n_r_ic_maxmag(), minc(), l_max(), nalias(), n_r_max(), m_max(), lm_max(), lmagmem(), n_r_maxmag(), n_phi_tot()): This module defines the grid points and the truncation

Variables

- readcheckpoints/l_axi_old[logical,private]
- readcheckpoints/lreads [logical,private]
- readcheckpoints/bytes_allocated[integer,private]
- readcheckpoints/n_start_file [integer,private]
- readcheckpoints/lreadr [logical,private]
- readcheckpoints/lreadxi[logical,private]

Subroutines and functions

This subroutine is used to read the old restart files produced by MagIC. This is now deprecated with the change of the file format. This is still needed to read old files.

- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,out]
- **dwdt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,out]
- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,out]
- **dzdt** (*ulm*-(*llm*)+1,*n_r_max*) [complex,out]
- \mathbf{p} (ulm-(llm)+1,n_r_max) [complex,out]
- **dpdt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*, *out*]
- **s** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*out*]
- **dsdt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*, *out*]
- xi (ulm-(llm)+1, n_r_max) [complex,out]
- **dxidt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*, *out*]
- **b** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,out]
- **dbdt** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,out]
- **aj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,out]
- **djdt** (*ulmmag-*(*llmmag*)+1,*n_r_maxmag*) [*complex*, *out*]
- **b_ic** (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
- **dbdt_ic** (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
- **aj_ic** (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]

```
• djdt_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
                • omega_ic [real,out]
               • omega_ma [real,out]
                • lorentz_torque_ic [real,out]
                • lorentz torque ma [real,out]
                • time [real,out]
               • dt_old [real,out]
                • dt_new [real,out]
                • n_time_step [integer,out]
          Called from getstartfields()
          Call to abortrun(),
                                               get1m21mo(),
                                                                             mapdatahydro(),
              scatter_from_rank0_to_lo(), mapdatamag()
subroutine readcheckpoints/readstartfields(w, dwdt, z, dzdt, p, dpdt, s, dsdt, xi, dxidt, b,
                                                       dbdt, aj, djdt, b_ic, dbdt_ic, aj_ic, djdt_ic,
                                                       omega_ic, omega_ma, lorentz_torque_ic,
                                                       lorentz_torque_ma, time, dt_old, dt_new,
```

n_time_step)

This subroutine is used to read the restart files produced by MagIC.

- \mathbf{w} (ulm-(llm)+1, n_r_max) [complex,out]
- **dwdt** (*ulm*-(*llm*)+1,*n_r_max*) [complex,out]
- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*out*]
- **dzdt** (ulm-(llm)+1,n_r_max) [complex,out]
- **p** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*, *out*]
- **dpdt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*, *out*]
- **s** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*, *out*]
- **dsdt** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*, *out*]
- **xi** (*ulm*-(*llm*)+1,*n_r_max*) [*complex*,*out*]
- **dxidt** (ulm-(llm)+1,n_r_max) [complex,out]
- \mathbf{b} (ulmmag-(llmmag)+1, n_r_maxmag) [complex,out]
- **dbdt** (*ulmmag-(llmmag)+1,n_r_maxmag*) [*complex,out*]
- **aj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,out]
- **djdt** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,out]
- $\bullet \ \ \mathbf{b_ic} \ (ulmmag\text{-}(llmmag)\text{+}1, n_r_ic_maxmag) \ [complex, out]$
- **dbdt_ic** (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
- aj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
- **djdt_ic** (*ulmmag-(llmmag)+1,n_r_ic_maxmag*) [*complex,out*]

- omega_ic [real,out]
- omega_ma [real,out]
- lorentz_torque_ic [real,out]
- lorentz_torque_ma [real,out]
- **time** [real,out]
- **dt old** [real,out]
- **dt_new** [real,out]
- n_time_step [integer,out]

Called from getstartfields()

Call to abortrun(), getlm2lmo(), maponefield(), scatter_from_rank0_to_lo()

Parameters

- n_r_max [integer,in]
- n_r_max_old [integer,in]
- l_max [integer,in]
- l_max_old [integer,in]
- m_max [integer,in]
- minc [integer,in]
- minc_old [integer,in]
- **inform** [integer,in]
- lm_max [integer,in]
- lm_max_old [integer,out]
- n_data_oldp [integer,out]
- **lm2lmo** (*lm_max*) [integer,out]

Called from readstartfields_old(), readstartfields()

- **wo** (*) [complex,in]
- scale_w [real,in]
- **r_old** (*) [real,in]
- lm2lmo (lm_max) [integer,in]
- n_r_max_old [integer,in]
- lm_max_old [integer,in]
- n_r_maxl [integer,in]

- dim1 [integer,in]
- **lbc1** [logical,in]
- l_ic [logical,in]
- w (lm_max,dim1) [complex,out]

Called from readstartfields()

Call to mapdatar()

subroutine readcheckpoints/mapdatahydro (wo, zo, po, so, xio, r_old, lm2lmo, n_r_max_old, lm_max_old, n_r_maxl, lbc1, lbc2, lbc3, lbc4, lbc5, w, z, p, s, xi)

Parameters

- **wo** (*) [complex,in]
- **zo** (*) [complex,in]
- **po** (*) [complex,in]
- so (*) [complex,in]
- **xio** (*) [complex,in]
- **r_old** (*) [real,in]
- lm2lmo (lm_max) [integer,in]
- n_r_max_old [integer,in]
- lm_max_old [integer,in]
- n_r_maxl [integer,in]
- **lbc1** [logical,in]
- **lbc2** [logical,in]
- **lbc3** [logical,in]
- **lbc4** [logical,in]
- **lbc5** [logical,in]
- w (lm_max,n_r_max) [complex,out]
- **z** (lm_max,n_r_max) [complex,out]
- **p** (lm_max,n_r_max) [complex,out]
- **s** (lm_max,n_r_max) [complex,out]
- **xi** (lm_max,n_r_max) [complex,out]

Called from readstartfields_old()

Call to mapdatar()

- wo (n_data_oldp) [complex,in]
- **zo** (n_data_oldp) [complex,in]

- **po** (n_data_oldp) [complex,in]
- so (n_data_oldp) [complex,in]
- **r_old** (*) [real,in]
- n_data_oldp [integer,in,]
- n_rad_tot [integer,in]
- n_r_max_old [integer,in]
- lm_max_old [integer,in]
- n_r_maxl [integer,in]
- lm2lmo (lm_max) [integer,in]
- dim1 [integer,in]
- l_ic [logical,in]
- w (lm_maxmag,dim1) [complex,out]
- **z** (*lm_maxmag*,dim1) [*complex*,out]
- **p** (*lm_maxmag*,dim1) [*complex,out*]
- **s** (*lm_maxmag*,dim1) [*complex*,out]

Called from readstartfields old()

Call to mapdatar()

subroutine readcheckpoints/mapdatar(datar, r_old , n_rad_tot , $n_r_max_old$, n_r_maxl , lbc, lic)

Copy (interpolate) data (read from disc file) from old grid structure to new grid. Linear interploation is used in r if the radial grid structure differs

called in mapdata

Parameters

- datar (*) [complex,inout]
- **r_old** (*) [real,in]
- n_rad_tot [integer,in]
- n_r_max_old [integer,in]
- n_r_maxl [integer,in]
- **lbc** [logical,in]
- l_ic [logical,in]

Called from mapdatahydro(), maponefield(), mapdatamag()

Call to polynomial_interpolation()

10.18.2 storeCheckPoints.f90

Description

This module contains several subroutines that can be used to store the checkpoint_#.tag files

Quick access

Routines store()

Needed modules

- parallel mod (rank ()): This module contains the blocking information
- init_fields (tomega_ic2(), tomega_ic1(), omegaosz_ic2(), omega_ic1(), omega_ma2(), omega_ma1(), omega_ic2(), inform(), omegaosz_ma1(), omegaosz_ma2(), tomega_ma1(), tomega_ma2(), omegaosz_ic1()): This module is used to construct the initial solution.
- fieldslast (d_omega_ma_dtlast(), d_omega_ic_dtlast(), lorentz_torque_iclast(), lorentz_torque_malast()): This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- output_data(n_log_file(), tag(), log_file()): This module contains the parameters for output control
- logic(l_save_out(), l_chemical_conv(), l_heat(), l_mag(), l_cond_ic()): Module containing the logicals that control the run
- lmloop_data(ulmmag(), llmmag(), llm(), ulm())
- precision_mod: This module controls the precision used in MagIC
- communications (gather_all_from_lo_to_rank0(), gt_ic(), gt_oc())
- num_param (alph1(), alph2(), tscale()): Module containing numerical and control parameters
- physical_parameters (pr(), prmag(), ek(), sigma_ratio(), radratio(), ra(), sc(), raxi()): Module containing the physical parameters
- charmanip (dble2str()): This module contains several useful routines to manipule character strings
- radial_functions (rscheme_oc()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- truncation(n_r_ic_max(), lm_maxmag(), n_r_ic_maxmag(), minc(), l_max(), nalias(), n_r_max(), fd_stretch(), lm_max(), n_theta_max(), n_r_maxmag(), fd_ratio(), n_phi_tot()): This module defines the grid points and the truncation

Variables

Subroutines and functions

This subroutine stores the results in a checkpoint file. In addition to the magnetic field and velocity potentials we also store the time derivative terms djdt(lm,nR),dbdt(lm,nR), ... to allow to restart with 2nd order Adams-Bashforth scheme. To minimize the memory imprint, a gater/write strategy has been adopted here. This implies that only one global array dimension(lm_max,n_r_max) is required.

Parameters

- time [real,in]
- dt [real,in]
- dtnew [real,in]
- n_time_step [integer,in]
- l_stop_time [logical,in]
- l_new_rst_file [logical,in]
- l_ave_file [logical,in]
- **w** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **p** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- \mathbf{s} (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **xi** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **b** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **aj** (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
- **b_ic** (*ulmmag-(llmmag)+1,n_r_ic_maxmag*) [*complex,in*]
- aj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,in]
- **dwdtlast** (*ulm*-(*llm*)+1,*n_r_max*) [*complex*,*in*]
- **dzdtlast** (*ulm*-(*llm*)+1,*n_r_max*) [*complex*,*in*]
- **dpdtlast** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **dsdtlast** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [complex,in]
- **dxidtlast** (*ulm*-(*llm*)+1,*n*_*r*_*max*) [*complex*,*in*]
- **dbdtlast** (*ulmmag*-(*llmmag*)+1,*n_r_maxmag*) [*complex*,*in*]
- **djdtlast** (*ulmmag*-(*llmmag*)+1,*n_r_maxmag*) [*complex*,*in*]
- **dbdt_iclast** (*ulmmag-*(*llmmag*)+1,*n_r_ic_maxmag*) [*complex*,*in*]
- **djdt_iclast** (*ulmmag-(llmmag*)+1,*n_r_ic_maxmag*) [*complex*,*in*]

Called from fields_average(), output()

Call to dble2str(), gather_all_from_lo_to_rank0()

10.19 Useful additional libraries

10.19.1 useful.f90

Description

library with several useful subroutines

Quick access

Needed modules

- precision_mod: This module controls the precision used in MagIC
- parallel_mod: This module contains the blocking information
- logic (l_save_out ()): Module containing the logicals that control the run
- constants (one (), two (), half ()): module containing constants and parameters used in the code.
- output_data (n_log_file(), log_file()): This module contains the parameters for output control

Variables

• useful/get_mean_sd[public]

Subroutines and functions

```
function useful/1_correct_step (n, t, t_last, n_max, n_step, n_intervals, n_ts, times, n_eo)
           Parameters
                 • n [integer,in] :: current step
                 • t [real,in] :: time at current step
                 • t_last [real,in] :: last time at current step
                 • n_max [integer,in] :: max number of steps
                 • n_step [integer,in] :: action interval
                 • n_intervals [integer,in] :: number of actions
                 • n_ts [integer,in] :: number of times t
                 • times (*) [real,in] :: times where l_correct_step == true
                 • n eo [integer,in] :: even/odd controller
           Return l_correct_step [logical]
           Called from step_time()
           Call to abortrun()
function useful/random(r)
           random number generator
           if (r == 0) then random(r) = next random number (between 0. and 1.)
```

if (r < 0) then random(r) = previous random number

```
if (r > 0) then
             random(r) = a new sequence of random numbers is started with seed r mod 1 note: r must
                 be a non-integer to get a different seq
         called in sinit
         Parameters r [real,in]
         Return random [real]
         Called from initb(), initv(), inits(), initxi()
subroutine useful/factorise(n, n_facs, fac, n_factors, factor)
         Purpose of this subroutine is factorize n into a number of given factors fac(i).
         Parameters
               • n [integer,in] :: number to be factorised!
               • n facs [integer,in] :: number of facs to be tried!
               • fac (*) [integer,in] :: list of fators to be tried!
               • n_factors [integer,out] :: number of factors used
               • factor (*) [integer,out] :: list of factors used
         Called from init fft()
         Call to abortrun()
function useful/cc2real(c, m)
         Parameters
               • c [complex,in]
               • m [integer,in]
         Return cc2real [real]
         Called from getstartfields(), get_power(),
                                                               hintrms(),
                                                                               rbrspec().
             get_amplitude(), hint2dpollm(), hint2pollm(), get_poltorrms(),
             get_e_mag(), outpar(), hint2dpol(), get_u_square(), spectrum(),
                                                 hint2tor(), rbpspec(),
             hint2torlm(), hint2pol(),
                                                                                 getdlm(),
             get_e_kin(), spectrum_temp()
function useful/cc22real (c1, c2, m)
         Parameters
               • c1 [complex,in]
               • c2 [complex,in]
               • m [integer,in]
         Return cc22real [real]
         Called from get_power(), get_e_mag(), spectrum()
subroutine useful/logwrite(message)
         Parameters message [character,in]
```

```
Called from getstartfields(), outto(), get_fd_grid(), step_time(),
   output(), radial(), initialize_blocking(), precalc(), dt_courant()
```

subroutine useful/get_mean_sd_vector(mean, sd, x, n, dt, totaltime)

This subroutine computes the mean and standard deviation according to a method introduced by Donald Knuth (1962). I rederived his formulas for a variable time step. On output SD still needs to be normalized with the totalTime and then you have to take the square root!! The input integer counts the number of calls. For n=1 initialisation is necessary.

Parameters

- mean (*) [real,inout]
- **sd** (*) [real,inout]
- **x** (*) [real,in]
- **n** [integer,in] :: number of calls(only n=1 needed)
- dt [real,in] :: time since last averaging step
- totaltime [real,in]:: total averaging time up to now

subroutine useful/get_mean_sd_scalar (mean, sd, x, n, dt, totaltime)

This subroutine computes the mean and standard deviation according to a method introduced by Donald Knuth (1962). I rederived his formulas for a variable time step. On output SD still needs to be normalized with the totalTime and then you have to take the square root!! The input integer counts the number of calls. For n=1 initialisation is necessary.

Parameters

- **mean** [real,inout] :: Time-average
- sd [real,inout] :: Standard-deviation
- x [real,in] :: quantity to be averaged
- **n** [integer,in] :: number of calls(only n=1 needed)
- dt [real,in] :: time since last averaging step
- totaltime [real,in]:: total averaging time up to now

subroutine useful/polynomial_interpolation(xold, yold, xnew, ynew)

Parameters

- **xold** (4) [real,in]
- yold (4) [complex,in]
- **xnew** [real,in]
- ynew [complex,out]

Called from mapdatar()

Call to polynomial_interpolation_real()

subroutine useful/polynomial_interpolation_real (xold, yold, xnew, ynew)

- **xold** (*) [real,in]
- yold (*) [real,in]
- xnew [real,in]

```
• ynew [real,out]
```

```
Called from polynomial interpolation()
```

Call to abortrun()

subroutine useful/abortrum(message)

This routine properly terminates a run

Parameters message [character,in]

```
Called from 1_correct_step(),
                         transportproperties(),
                                                updateb(),
  get_lorder_lm_blocking(),
                              get_b_nl_bcs(),
                                                   outto(),
                                  get_p0mat(), get_fd_grid(),
  readnamelists(), fftjw(), factorise(), init_fft(), lnpas2tr(),
  readstartfields_old(),
                                     initb(),
                       wpass3jw(),
                                                   inits(),
  get_subblocks(), polynomial_interpolation_real(),
                                                   initxi(),
  get_snake_lm_blocking(), get_wpsmat(), init_rnb(), get_zmat(),
  prepare_mat(), pt_cond(), checktruncation(), get_wptmat(),
  get_wmat(), wpass5jw(), get_ps0mat(), xi_cond(), getdlm(),
  lo2lm_redist(), readstartfields(), writeinfo(), plm_theta(),
  get_pt0mat(), ps_cond(), get_wpmat(), j_cond(), chebintinit(),
  get_bmat(), sendvals_to_rank0(), movie_gather_frames_to_rank0(),
  write movie frame(), get smat(), getbackground(), lm2lo redist(),
  get_ximat(), get_xi0mat(), get_movie_type(), initialize_blocking(),
  get z10mat(), precalc(), legtf()
```

function useful/round_off(param, ref)

Parameters

- param [real,in] :: parameter to be checked
- **ref** [real,in] :: reference value

Return round_off [real]

Called from get_power()

10.19.2 mem_alloc.f90

Description

This little module is used to estimate the global memory allocation used in MagIC

Quick access

Needed modules

- parallel_mod: This module contains the blocking information
- precision_mod (cp(), lip()): This module controls the precision used in MagIC
- output_data(tag()): This module contains the parameters for output control

Variables

```
mem_alloc/bytes_allocated[integer,public]
```

```
• mem_alloc/ranks_selected(:)[integer,private/allocatable]
```

```
• mem_alloc/n_memory_file [integer,private]
```

- mem_alloc/memory_file [character,private]
- mem_alloc/n_ranks_print [integer,private]

Subroutines and functions

```
subroutine mem_alloc/initialize_memory_counter()
        Called from magic
subroutine mem alloc/memwrite(origin, bytes alloc)
        Parameters
              • origin [character,in]
             • bytes_alloc [integer,in]
        Called from initialize radialloop(),
                                                              initialize_lmloop(),
            initialize_step_time(),
                                                     initialize_communications(),
            initialize_blocking(), magic
        Call to human_readable_size()
subroutine mem_alloc/finalize_memory_counter()
        Called from magic
        Call to human_readable_size()
function mem_alloc/human_readable_size(bytes)
        Parameters bytes [integer,in]
        Return st [real]
        Called from memwrite(), finalize_memory_counter()
10.19.3 char_manip.f90
```

Description

This module contains several useful routines to manipule character strings

Quick access

```
Routines dble2str(), capitalize(), str2dble(), delete_string(), length_to_blank(), length_to_char()
```

Needed modules

• precision_mod: This module controls the precision used in MagIC

Subroutines and functions

```
subroutine charmanip/capitalize(string_bn)
```

Convert lower-case letters into capital letters

Parameters string_bn [character,inout]

Called from readnamelists(), step_time(), get_movie_type()

subroutine charmanip/delete_string(string_bn, string_del, length)

Deletes string_del from string and returns new length of string.

Parameters

- **string_bn** [character,inout]
- **string_del** [character,in]
- length [integer,out]

Called from get_movie_type()

```
subroutine charmanip/str2dble(string_bn, num)
```

interprets next word in string as an 1 real number deletes leading blanks and next_word from string

Parameters

- string_bn [character,in]
- **num** [real,out] :: output

Called from get_movie_type()

function charmanip/length_to_blank(string_bn)

determines number of characters before first blank in string

Parameters string_bn [character,in]

Return length_to_blank [integer]

Called from readnamelists(), writenamelists(), get_movie_type()

function charmanip/length_to_char(string_bn, char_bn)

Parameters

• string_bn [character,in]

• char_bn [character,in]

Return length_to_char [integer]

subroutine charmanip/dble2str(num, str)

converts a 1 number num into a character str

Parameters

- num [real,in]
- **str** [character,out]

Called from step_time(), store()

FORTRAN MODULE INDEX

a	
algebra, 304	leg_helper_mod, 289
b	legendre_grid_to_spec, 297
blocking, 314	<pre>legendre_spec_to_grid, 292 lmloop_data, 211</pre>
-	lmloop_mod, 243
C	lmmapping, 317
charmanip, 427 chebint_mod, 406	logic, 193
chebyshev_polynoms_mod, 282	m
communications, 212	magnetic_energy, 327
constants, 206 cosine_transform_even, 285	mem_alloc, 426 movie_data, 351
cosine_transform_odd, 283	movie_data, 331
courant_mod, 239	n
d	namelists, 218
dtb_arrays_mod,386	nl_special_calc, 409 nonlinear_bcs, 280
dtb_mod, 382	nonlinear_lm_mod, 277
f	num_param, 186
I	
CCL 200	0
fft, 299 fft, fac mod, 287	O omega, 408
fft, 299 fft_fac_mod, 287 fields, 198	O omega, 408 out_coeff, 367
<pre>fft_fac_mod, 287 fields, 198 fields_average_mod, 370</pre>	omega, 408 out_coeff, 367 out_dtb_frame, 387
fft_fac_mod, 287 fields, 198	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359
<pre>fft_fac_mod, 287 fields, 198 fields_average_mod, 370</pre>	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359 out_movie_ic, 366
<pre>fft_fac_mod, 287 fields, 198 fields_average_mod, 370 fieldslast, 200</pre>	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359
<pre>fft_fac_mod, 287 fields, 198 fields_average_mod, 370 fieldslast, 200 g general_arrays_mod, 277 geos_mod, 402</pre>	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359 out_movie_ic, 366 outmisc_mod, 331 outpar_mod, 338 output_data, 201
<pre>fft_fac_mod, 287 fields, 198 fields_average_mod, 370 fieldslast, 200 general_arrays_mod, 277 geos_mod, 402 getdlm_mod, 330</pre>	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359 out_movie_ic, 366 outmisc_mod, 331 outpar_mod, 338 output_data, 201 output_mod, 319
fft_fac_mod, 287 fields, 198 fields_average_mod, 370 fieldslast, 200 general_arrays_mod, 277 geos_mod, 402 getdlm_mod, 330 graphout_mod, 348	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359 out_movie_ic, 366 outmisc_mod, 331 outpar_mod, 338 output_data, 201 output_mod, 319 outrot, 334
<pre>fft_fac_mod, 287 fields, 198 fields_average_mod, 370 fieldslast, 200 general_arrays_mod, 277 geos_mod, 402 getdlm_mod, 330</pre>	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359 out_movie_ic, 366 outmisc_mod, 331 outpar_mod, 338 output_data, 201 output_mod, 319 outrot, 334 outto_mod, 396
fft_fac_mod, 287 fields, 198 fields_average_mod, 370 fieldslast, 200 general_arrays_mod, 277 geos_mod, 402 getdlm_mod, 330 graphout_mod, 348	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359 out_movie_ic, 366 outmisc_mod, 331 outpar_mod, 338 output_data, 201 output_mod, 319 outrot, 334 outto_mod, 396 p
<pre>fft_fac_mod, 287 fields, 198 fields_average_mod, 370 fieldslast, 200 g general_arrays_mod, 277 geos_mod, 402 getdlm_mod, 330 graphout_mod, 348 h</pre>	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359 out_movie_ic, 366 outmisc_mod, 331 outpar_mod, 338 output_data, 201 output_mod, 319 outrot, 334 outto_mod, 396 p parallel_mod, 209
<pre>fft_fac_mod, 287 fields, 198 fields_average_mod, 370 fieldslast, 200 g general_arrays_mod, 277 geos_mod, 402 getdlm_mod, 330 graphout_mod, 348 h</pre>	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359 out_movie_ic, 366 outmisc_mod, 331 outpar_mod, 338 output_data, 201 output_mod, 319 outrot, 334 outto_mod, 396 p
<pre>fft_fac_mod, 287 fields, 198 fields_average_mod, 370 fieldslast, 200 g general_arrays_mod, 277 geos_mod, 402 getdlm_mod, 330 graphout_mod, 348 h horizontal_data, 232 i</pre>	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359 out_movie_ic, 366 outmisc_mod, 331 outpar_mod, 338 output_data, 201 output_mod, 319 outrot, 334 outto_mod, 396 p parallel_mod, 209 physical_parameters, 189 plms_theta, 288 power, 341
<pre>fft_fac_mod, 287 fields, 198 fields_average_mod, 370 fieldslast, 200 g general_arrays_mod, 277 geos_mod, 402 getdlm_mod, 330 graphout_mod, 348 h horizontal_data, 232 i init_fields, 221</pre>	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359 out_movie_ic, 366 outmisc_mod, 331 outpar_mod, 338 output_data, 201 output_mod, 319 outrot, 334 outto_mod, 396 p parallel_mod, 209 physical_parameters, 189 plms_theta, 288 power, 341 precalculations, 226
<pre>fft_fac_mod, 287 fields, 198 fields_average_mod, 370 fieldslast, 200 g general_arrays_mod, 277 geos_mod, 402 getdlm_mod, 330 graphout_mod, 348 h horizontal_data, 232 i init_fields, 221 integration, 313</pre>	omega, 408 out_coeff, 367 out_dtb_frame, 387 out_movie, 359 out_movie_ic, 366 outmisc_mod, 331 outpar_mod, 338 output_data, 201 output_mod, 319 outrot, 334 outto_mod, 396 p parallel_mod, 209 physical_parameters, 189 plms_theta, 288 power, 341

```
r
radial\_data, 210
radial_der, 306
radial_der_even,310
radial_functions, 229
radial_spectra,400
radialloop, 266
readcheckpoints, 415
riteration_mod, 269
riterthetablocking_mod, 271
riterthetablocking_openmp_mod, 273
{\tt rms\_helpers}, 378
S
special, 207
spectra, 343
start_fields, 219
step_time_mod, 235
storecheckpoints, 420
t
timing, 240
to arrays mod, 396
to_helpers, 394
torsional_oscillations, 390
truncation, 184
u
updateb_mod, 263
updates_mod, 258
updatewp_mod, 251
updatewps_mod, 245
updatewpt_mod, 248
updatexi_mod, 261
updatez_mod, 255
useful, 422
```

432 Fortran Module Index

PYTHON MODULE INDEX

m

```
magic.bLayers, 162
magic.coeff, 149
magic.cyl, 164
magic.graph2vtk, 159
magic.libmagic, 173
magic.plotlib, 171
magic.potExtra, 161
magic.spectralTransforms, 169
```

434 Python Module Index

INDEX

Symbols	advrmssd (fortran variable in module rms), 375
('general_arrays_mod/unknown_type', None) (fortran	aj_ave (fortran variable in module fields_average_mod),
type in module general_arrays_mod), 277	371
add() (magic.Butterfly method), 168	aj_ave_global (fortran variable in module
add() (magic.Movie method), 147	fields_average_mod), 372
add() (magic.coeff.MagicCoeffCmb method), 149	aj_ic (fortran variable in module fields), 198
init() (magic.AvgField method), 139	aj_ic_ave (fortran variable in module
init() (magic.Butterfly method), 168	fields_average_mod), 372
init() (magic.CompSims method), 158	aj_ic_lmloc (fortran variable in module fields), 200
init() (magic.MagicGraph method), 142	aj_lmloc (fortran variable in module fields), 198
init() (magic.MagicPV method), 157	aj_rloc (fortran variable in module fields), 200
init() (magic.MagicPotential method), 153	alffac (fortran variable in module num_param), 188
init() (magic.MagicRSpec method), 153	algebra (module), 304
init() (magic.MagicRadial method), 140	allocate_common_arrays() (fortran subroutine in module
init() (magic.MagicSetup method), 138	riterthetablocking_mod), 272
init() (magic.MagicSpectrum method), 141	allocate_mappings() (fortran subroutine in module
init() (magic.MagicSpectrum2D method), 141	lmmapping), 319
init() (magic.MagicTOHemi method), 157	allocate_subblocks_mappings() (fortran subroutine in
init() (magic.MagicTOZ method), 156	module Immapping), 319
init() (magic.MagicTaySphere method), 157	alph1 (fortran variable in module num_param), 187
init() (magic.MagicTs method), 139	alph2 (fortran variable in module num_param), 187
init() (magic.Movie method), 147	alpha (fortran variable in module num_param), 188
init() (magic.Movie3D method), 149	alpha0 (fortran variable in module radial_functions), 231
init() (magic.Surf method), 143	alpha1 (fortran variable in module radial_functions), 230
init() (magic.TOMovie method), 156	alpha2 (fortran variable in module radial_functions), 230
init() (magic.ThetaHeat method), 164	am_kpol_file (fortran variable in module spectra), 345
init() (magic.bLayers.BLayers method), 162	am_ktor_file (fortran variable in module spectra), 346
init() (magic.coeff.MagicCoeffCmb method), 149	am_mpol_file (fortran variable in module spectra), 345
init() (magic.coeff.MagicCoeffR method), 151	am_mtor_file (fortran variable in module spectra), 345
init() (magic.cyl.Cyl method), 165	amp_b1 (fortran variable in module init_fields), 222 amp_curr (fortran variable in module special), 208
init() (magic.graph2vtk.Graph2Vtk method), 159	amp_imp (fortran variable in module special), 208
init() (magic.potExtra.ExtraPot method), 161	amp_riicasym (fortran variable in module special), 208
str() (magic.AvgField method), 140	amp_riicsym (fortran variable in module special), 208
str() (magic.ThetaHeat method), 164	amp_rimaasym (fortran variable in module special), 208
str() (magic.bLayers.BLayers method), 162	amp_rimasym (fortran variable in module special), 209
Α	amp_s1 (fortran variable in module init_fields), 224
	amp_s2 (fortran variable in module init_fields), 223
abortrun() (fortran subroutine in module useful), 426	amp_v1 (fortran variable in module init_fields), 223
addtime() (fortran subroutine in module timing), 242	amp_xi1 (fortran variable in module init_fields), 223
adv2hint (fortran variable in module rms), 375	amp_xi2 (fortran variable in module init_fields), 223
advrmsl_sd (fortran variable in module rms), 375	ampstrat (fortran variable in module physi-
advrmsl_ta (fortran variable in module rms), 374	amportat (tortian variable in module physi-

cal_parameters), 189 amstart (fortran variable in module num_param), 187	botxi (fortran variable in module init_fields), 223 botxicond (fortran variable in module start_fields), 220
anelastic_flavour (fortran variable in module	bpeakbot (fortran variable in module init_fields), 223
num_param), 188	bpeaktop (fortran variable in module init_fields), 223
anelprof() (in module magic.libmagic), 173	bpivot (fortran variable in module updateb_mod), 264
angular_file (fortran variable in module outrot), 335	bpsdas_rloc (fortran variable in module tor-
arc2hint (fortran variable in module rms), 375	sional_oscillations), 391
arcmag2hint (fortran variable in module rms), 375	bpsdlmr (fortran variable in module outto_mod), 398
arcmagrmsl_sd (fortran variable in module rms), 375	bpsdlmr_rloc (fortran variable in module outto_mod), 399
arcmagrmsl_ta (fortran variable in module rms), 376	bpzas_rloc (fortran variable in module tor-
arcmagrmssd (fortran variable in module rms), 376	sional_oscillations), 391
arcrmsl_sd (fortran variable in module rms), 375	bpzdas_rloc (fortran variable in module tor-
arcrmsl_ta (fortran variable in module rms), 376	sional_oscillations), 391
arcrmssd (fortran variable in module rms), 375	bpzdlmr (fortran variable in module outto_mod), 398
array_of_statuses (fortran variable in module communi-	bpzdlmr_rloc (fortran variable in module outto_mod), 399
cations), 213	bpzlmr (fortran variable in module outto_mod), 398
astrm (fortran variable in module outto_mod), 399	bpzlmr_rloc (fortran variable in module outto_mod), 399
astrm_sloc (fortran variable in module outto_mod), 398	bs2as_rloc (fortran variable in module tor-
avg() (magic.cyl.Cyl method), 165	sional_oscillations), 391
avg() (magic.MagicPotential method), 154	bs2lmr (fortran variable in module outto_mod), 399
avg() (magic.potExtra.ExtraPot method), 161	bs2lmr_rloc (fortran variable in module outto_mod), 399
avg() (magic.Surf method), 143	bspas_rloc (fortran variable in module tor-
AvgField (class in magic), 139	sional_oscillations), 391
avgField() (in module magic.libmagic), 173	bspdas_rloc (fortran variable in module torsional_oscillations), 391
avgStd() (magic.Movie method), 147 avgz() (magic.cyl.Cyl method), 165	bspdlmr (fortran variable in module outto_mod), 398
avgz() (magic.cyi.Cyi method), 103	bspdlmr_rloc (fortran variable in module outto_mod), 399
В	bsplmr (fortran variable in module outto_mod), 398
	bsplmr_rloc (fortran variable in module outto_mod), 398
b (fortran variable in module fields), 200	bszas_rloc (fortran variable in module tor-
b0 (fortran variable in module special), 208	sional_oscillations), 392
b_ave (fortran variable in module fields_average_mod),	bszlmr (fortran variable in module outto_mod), 399
371 b_ave_global (fortran variable in module	bszlmr_rloc (fortran variable in module outto_mod), 398
	buo (fortran variable in module updatewp_mod), 253
fields_average_mod), 372 b_ic (fortran variable in module fields), 199	buo (fortran variable in module updatewps_mod), 246
b_ic_ave (fortran variable in module neds), 199	buo (fortran variable in module updatewpt_mod), 249
fields_average_mod), 371	buo2hint (fortran variable in module rms), 376
b_ic_lmloc (fortran variable in module fields), 200	buo_chemr_mean (fortran variable in module power), 342
b_lmloc (fortran variable in module fields), 199	buo_chemr_sd (fortran variable in module power), 342
b_r_file (fortran variable in module output_mod), 323	buofac (fortran variable in module physical_parameters),
b_rloc (fortran variable in module fields), 198	192
bcmb (fortran variable in module magnetic_energy), 328	buor_mean (fortran variable in module power), 342
beta (fortran variable in module radial_functions), 231	buor_sd (fortran variable in module power), 342
bic (fortran variable in module special), 208	buormsl_sd (fortran variable in module rms), 374
bicb (fortran variable in module fields_average_mod),	buormsl_ta (fortran variable in module rms), 375
371	buormssd (fortran variable in module rms), 375
bicb (fortran variable in module output_mod), 322	Butterfly (class in magic), 168
BLayers (class in magic.bLayers), 162	bytes_allocated (fortran variable in module mem_alloc),
blocking (module), 314	427
bmat (fortran variable in module updateb_mod), 265	bytes_allocated (fortran variable in module readcheck-
bmat_fac (fortran variable in module updateb_mod), 264	
	points), 416
bmax imp (fortran variable in module special). 208	· ·
bmax_imp (fortran variable in module special), 208 botcond (fortran variable in module start_fields), 220	points), 416

bzpdlmr_rloc (fortran variable in module outto_mod), 399	ciarmsl_sd (fortran variable in module rms), 376
C	ciarmsl_ta (fortran variable in module rms), 375 ciarmssd (fortran variable in module rms), 376
c_dt_z10_ic (fortran variable in module constants), 206	clf2hint (fortran variable in module rms), 375
c_dt_z10_ma (fortran variable in module constants), 207	clfrmsl_sd (fortran variable in module rms), 376
c_lorentz_ic (fortran variable in module constants), 206	clfrmsl_ta (fortran variable in module rms), 375
c_lorentz_ma (fortran variable in module constants), 207	clfrmssd (fortran variable in module rms), 375
c_moi_ic (fortran variable in module constants), 207	clm (fortran variable in module outto_mod), 398
c_moi_ma (fortran variable in module constants), 207	clm_sloc (fortran variable in module outto_mod), 398
c_moi_oc (fortran variable in module constants), 206	cmb_file (fortran variable in module output_mod), 323
c_z10_omega_ic (fortran variable in module constants),	cmbhflux (fortran variable in module physi-
206	cal_parameters), 192
c_z10_omega_ma (fortran variable in module constants), 206	cmbmov_file (fortran variable in module output_mod), 323
cacheblock_size_in_b (fortran variable in module block-	codeversion (fortran variable in module constants), 207
ing), 316	communications (module), 212
capitalize() (fortran subroutine in module charmanip),	CompSims (class in magic), 158
428	con_decrate (fortran variable in module physi-
cc22real() (fortran function in module useful), 424	cal_parameters), 192
cc2real() (fortran function in module useful), 424	con_funcwidth (fortran variable in module physi-
charmanip (module), 427	cal_parameters), 191
cheb_grid() (fortran subroutine in module cheby-	con_lambdamatch (fortran variable in module physi-
shev_polynoms_mod), 283	cal_parameters), 192
cheb_ic (fortran variable in module radial_functions), 231	con_lambdaout (fortran variable in module physi-
cheb_int (fortran variable in module radial_functions),	cal_parameters), 193
230	con_radratio (fortran variable in module physi-
cheb_int_ic (fortran variable in module radial_functions),	cal_parameters), 190
230	conductance_ma (fortran variable in module physical parameters) 102
cheb_norm_ic (fortran variable in module ra-	cal_parameters), 192 constants (module), 206
dial_functions), 230	cor00_fac (fortran variable in module updatewps_mod),
chebgrid() (in module magic.libmagic), 174	246
chebint() (fortran function in module chebint_mod), 407	cor00_fac (fortran variable in module updatewpt_mod),
chebint_mod (module), 406 chebint_d() (fortron function in module shekint mod), 407	249
chebintd() (fortran function in module chebint_mod), 407 chebintinit() (fortran subroutine in module chebint_mod),	cor2hint (fortran variable in module rms), 376
407	corfac (fortran variable in module physical_parameters),
chebt_ic (fortran variable in module radial_functions),	191
231	corm (fortran variable in module outto_mod), 399
chebt_ic_even (fortran variable in module ra-	corm_sloc (fortran variable in module outto_mod), 399
dial_functions), 231	corrmsl_sd (fortran variable in module rms), 376
chebt_z (fortran variable in module geos_mod), 403	corrmsl_ta (fortran variable in module rms), 374
chebt_z (fortran variable in module outto_mod), 398	corrmssd (fortran variable in module rms), 375
chebyshev_polynoms_mod (module), 282	cos36 (fortran variable in module constants), 207
check_mpi_error() (fortran subroutine in module paral-	cos72 (fortran variable in module constants), 207
lel_mod), 210	cosine_transform_even (module), 285
check_time_hits() (fortran subroutine in module	cosine_transform_odd (module), 283
step_time_mod), 238	cosn2 (fortran variable in module horizontal_data), 234
checktruncation() (fortran subroutine in module trunca-	costf1_complex() (fortran subroutine in module co-
tion), 186	sine_transform_odd), 284
chemfac (fortran variable in module physi-	costf1_complex_1d() (fortran subroutine in module co-
cal_parameters), 190	sine_transform_odd), 284
chunksize (fortran variable in module parallel_mod), 210	costf1_real() (fortran subroutine in module co-
ci (fortran variable in module constants), 206	sine_transform_odd), 285

cia2hint (fortran variable in module rms), 374

costf1_real_1d() (fortran subroutine in module co-	dbdt_rloc_container (fortran variable in module step_time_mod), 237
sine_transform_odd), 285 costf2() (fortran subroutine in module co-	dbdtlast_lmloc (fortran variable in module fieldslast), 201
sine_transform_even), 286	dbeta (fortran variable in module radial_functions), 230
costf_arrays() (fortran subroutine in module geos_mod),	dble2str() (fortran subroutine in module charmanip), 429
406	dcheb_ic (fortran variable in module radial_functions),
costheta (fortran variable in module horizontal_data), 233	230
courant() (fortran subroutine in module courant_mod),	ddb0 (fortran variable in module special), 208
239	ddb_ic (fortran variable in module fields), 199
courant_mod (module), 239	ddb_ic_lmloc (fortran variable in module fields), 199
courfac (fortran variable in module num_param), 188	ddb_lmloc (fortran variable in module fields), 199
cp (fortran variable in module precision_mod), 183 create_gather_type() (fortran subroutine in module com-	ddb_rloc (fortran variable in module fields), 200 ddbeta (fortran variable in module radial_functions), 231
munications), 215	dddw (fortran variable in module updatewp_mod), 252
create_lm2r_type() (fortran subroutine in module com-	ddj_ic (fortran variable in module fields), 200
munications), 215	ddj_ic_lmloc (fortran variable in module fields), 200
create_r2lm_type() (fortran subroutine in module com-	ddj_lmloc (fortran variable in module fields), 200
munications), 216	ddlalpha0 (fortran variable in module radial_functions),
cut() (in module magic.plotlib), 171	231
Cyl (class in magic.cyl), 164	ddltemp0 (fortran variable in module radial_functions),
cylSder() (in module magic.libmagic), 174	230
cylZder() (in module magic.libmagic), 174	ddlvisc (fortran variable in module radial_functions), 231 ddw_lmloc (fortran variable in module fields), 198
D	ddw_rloc (fortran variable in module fields), 198
d2cheb_ic (fortran variable in module radial_functions),	ddws_global (fortran variable in module geos_mod), 403
230	ddzasl (fortran variable in module torsional_oscillations),
d2temp0 (fortran variable in module radial_functions),	391
231	deallocate_common_arrays() (fortran subroutine in mod-
d_fft_init (fortran variable in module fft), 300	ule riterthetablocking_mod), 272
d_l (fortran variable in module horizontal_data), 234	deallocate_mappings() (fortran subroutine in module
d_lp1 (fortran variable in module horizontal_data), 234	lmmapping), 319
d_m (fortran variable in module horizontal_data), 234	deallocate_subblocks_mappings() (fortran subroutine in
d_mc2m (fortran variable in module horizontal_data), 234	module lmmapping), 319 defaultnamelists() (fortran subroutine in module
d_omega_ic_dtlast (fortran variable in module fieldslast), 201	namelists), 219
d_omega_ma_dtlast (fortran variable in module field-	delete_string() (fortran subroutine in module charmanip),
slast), 201	428
db0 (fortran variable in module special), 208	deltacond (fortran variable in module start_fields), 220
db_ave_global (fortran variable in module	deltaxicond (fortran variable in module start_fields), 220
fields_average_mod), 371	delxh2 (fortran variable in module num_param), 188
db_ic (fortran variable in module fields), 199	delxr2 (fortran variable in module num_param), 187
db_ic_lmloc (fortran variable in module fields), 199	dentropy0 (fortran variable in module radial_functions), 230
db_lmloc (fortran variable in module fields), 199	deriv() (in module magic.coeff), 152
db_rloc (fortran variable in module fields), 200 dbdt_cmb_lmloc (fortran variable in module	destroy_gather_type() (fortran subroutine in module com-
step_time_mod), 238	munications), 215
dbdt_iclast_lmloc (fortran variable in module fieldslast),	destroy_lm2r_type() (fortran subroutine in module com-
201	munications), 216
dbdt_lmloc (fortran variable in module step_time_mod),	destroy_r2lm_type() (fortran subroutine in module com-
237	munications), 216
dbdt_lmloc_container (fortran variable in module	dflowdt_lmloc_container (fortran variable in module
step_time_mod), 237	step_time_mod), 237
dbdt_rloc (fortran variable in module step_time_mod),	dflowdt_rloc_container (fortran variable in module step_time_mod), 238
237	σωρ_μπο_που <i>)</i> , 250

dif (fortran variable in module updatewp_mod), 253 dif (fortran variable in module updatewps_mod), 247 dif (fortran variable in module updatewpt_mod), 250 dif (fortran variable in module updatez_mod), 256 difchem (fortran variable in module num_param), 187	dlvu2meanr (fortran variable in module outpar_mod), 339 dmbmean (fortran variable in module output_mod), 322 dmvmean (fortran variable in module output_mod), 323 do_iteration_thetablocking_openmp() (fortran subroutine in module riterthetablocking_openmp_mod).
difeta (fortran variable in module num_param), 188	274
difexp (fortran variable in module physical_parameters),	dp_lmloc (fortran variable in module fields), 199
190	dp_rloc (fortran variable in module fields), 199
diff_prec_angle (fortran variable in module physical_parameters), 192	dpdt_lmloc (fortran variable in module step_time_mod), 237
difkap (fortran variable in module num_param), 187	dpdt_rloc (fortran variable in module step_time_mod),
difnu (fortran variable in module num_param), 187	237
difpol2hint (fortran variable in module rms), 375	dpdtlast_lmloc (fortran variable in module fieldslast), 201
difpollmr (fortran variable in module rms), 376	dphi (fortran variable in module horizontal_data), 233
difrmsl_sd (fortran variable in module rms), 376	dphi0 (fortran variable in module horizontal_data), 234
difrmsl_ta (fortran variable in module rms), 376	dphi02 (fortran variable in module horizontal_data), 233
difrmssd (fortran variable in module rms), 376	dpl0eq (fortran variable in module horizontal_data), 234
diftor2hint (fortran variable in module rms), 375	dplm (fortran variable in module horizontal_data), 233
dipcmbmean (fortran variable in module output_mod),	dplms (fortran variable in module geos_mod), 403
323	dplms (fortran variable in module outto_mod), 398
dipmean (fortran variable in module output_mod), 322	dplmspv (fortran variable in module geos_mod), 403
dipole_file (fortran variable in module magnetic_energy),	dplmz (fortran variable in module geos_mod), 403
328	dpvmean (fortran variable in module output_mod), 322
dissnb (fortran variable in module physical_parameters), 191	dr_fac_ic (fortran variable in module radial_functions), 231
divktemp0 (fortran variable in module radial_functions),	dr_facc (fortran variable in module rms), 376
231	driftbd_file (fortran variable in module outrot), 335
dj_ic (fortran variable in module fields), 199	driftbq_file (fortran variable in module outrot), 335
dj_ic_lmloc (fortran variable in module fields), 199	driftvd_file (fortran variable in module outrot), 335
dj_lmloc (fortran variable in module fields), 199	driftvq_file (fortran variable in module outrot), 335
dj_rloc (fortran variable in module fields), 199	ds_lmloc (fortran variable in module fields), 199
djdt_iclast_lmloc (fortran variable in module fieldslast),	ds_rloc (fortran variable in module fields), 199
201	dsdt_lmloc (fortran variable in module step_time_mod),
djdt_lmloc (fortran variable in module step_time_mod), 238	237
	dsdt_lmloc_container (fortran variable in module
djdt_rloc (fortran variable in module step_time_mod), 237	step_time_mod), 237 dsdt_rloc (fortran variable in module step_time_mod),
djdtlast_lmloc (fortran variable in module fieldslast), 201	237
dlalpha0 (fortran variable in module radial_functions),	dsdt_rloc_container (fortran variable in module
230	step_time_mod), 238
dlbmean (fortran variable in module output_mod), 322	dsdtlast_lmloc (fortran variable in module fieldslast), 201
dlh (fortran variable in module horizontal_data), 234	dt_bpot (fortran variable in module output_data), 206
dlkappa (fortran variable in module radial_functions), 230	dt_cmb (fortran variable in module output_data), 203
dllambda (fortran variable in module radial_functions),	dt_cmb_file (fortran variable in module output_mod), 322
230	dt_courant() (fortran subroutine in module courant_mod),
dltemp0 (fortran variable in module radial_functions),	240
231	dt_graph (fortran variable in module output_data), 203
dlvcmean (fortran variable in module output_mod), 323	dt_icb_l_ave (fortran variable in module spectra), 344
dlycmeanr (fortran variable in module outpar_mod), 339	dt_icb_l_sd (fortran variable in module spectra), 345
dlvisc (fortran variable in module radial_functions), 231	dt_icb_m_ave (fortran variable in module spectra), 345
dlymean (fortran variable in module output_mod), 321	dt_icb_m_sd (fortran variable in module spectra), 346
dlymeanr (fortran variable in module outpar_mod), 339	dt_log (fortran variable in module output_data), 203
dlvu2cmeanr (fortran variable in module outpar_mod),	dt_movie (fortran variable in module output_data), 203
339	dt. pot (fortran variable in module output, data) 204

dt_probe (fortran variable in module output_data), 202 dt_r_field (fortran variable in module output_data), 203	dvprlm_lmloc (fortran variable in module step_time_mod), 237
dt_rst (fortran variable in module output_data), 204 dt_spec (fortran variable in module output_data), 202	dvprlm_rloc (fortran variable in module step_time_mod),
dt_to (fortran variable in module output_data), 204	dvsrlm_lmloc (fortran variable in module
dt_tomovie (fortran variable in module output_data), 204	step_time_mod), 237
dt_toz (fortran variable in module output_data), 203	dvsrlm_rloc (fortran variable in module step_time_mod),
· · · · · · · · · · · · · · · · · · ·	dvsriii_rioc (fordaii variable ili iliodule step_tiile_iliod),
dt_tpot (fortran variable in module output_data), 202	
dt_vpot (fortran variable in module output_data), 203 dtb_arrays_mod (module), 386	dvxbhlm_lmloc (fortran variable in module step_time_mod), 238
dtb_from_rloc_to_lo() (fortran subroutine in module	dvxbhlm_rloc (fortran variable in module
dtb_mod), 384	step_time_mod), 237
dtb_gather_lo_on_rank0() (fortran subroutine in module	dvxirlm_lmloc (fortran variable in module
dtb_mod), 384	step_time_mod), 237
dtb_lmloc_container (fortran variable in module	dvxirlm_rloc (fortran variable in module step_time_mod),
dtb_mod), 383	238
dtb_mod (module), 382	dvxvhlm_lmloc (fortran variable in module
dtb_rloc_container (fortran variable in module dtb_mod),	step_time_mod), 237
383	dvxvhlm_rloc (fortran variable in module
dtbpol2hint (fortran variable in module rms), 374	step_time_mod), 238
dtbpollmr (fortran variable in module rms), 375	dw_ave_global (fortran variable in module
dtbrms() (fortran subroutine in module rms), 377	fields_average_mod), 372
dtbrms_file (fortran variable in module rms), 375	dw_lmloc (fortran variable in module fields), 199
dtbtor2hint (fortran variable in module rms), 375	dw_rloc (fortran variable in module fields), 199
dte_file (fortran variable in module output_mod), 322	dwdt_lmloc (fortran variable in module step_time_mod),
dteint (fortran variable in module output_mod), 323	237
dtheta1a (fortran variable in module horizontal_data), 234	dwdt_rloc (fortran variable in module step_time_mod),
dtheta1s (fortran variable in module horizontal_data), 234	237
dtheta2a (fortran variable in module horizontal_data), 234	dwdtlast_lmloc (fortran variable in module fieldslast), 201
dtheta2s (fortran variable in module horizontal_data), 234	dwold (fortran variable in module updatewp_mod), 253
dtheta3a (fortran variable in module horizontal_data), 234	dws_global (fortran variable in module geos_mod), 404
dtheta3s (fortran variable in module horizontal_data), 234	dxi_lmloc (fortran variable in module fields), 199
dtheta4a (fortran variable in module horizontal_data), 234	dxi_rloc (fortran variable in module fields), 198
dtheta4s (fortran variable in module horizontal_data), 234	dxidt_lmloc (fortran variable in module step_time_mod),
dtmax (fortran variable in module num_param), 188	237
dtmin (fortran variable in module num_param), 187	dxidt_lmloc_container (fortran variable in module
dtp (fortran variable in module updateb_mod), 265	step_time_mod), 238
dtstart (fortran variable in module num_param), 187	dxidt_rloc (fortran variable in module step_time_mod),
dtt (fortran variable in module updateb_mod), 265	237
dtv (fortran variable in module updatewp_mod), 253	dxidt_rloc_container (fortran variable in module
dtv (fortran variable in module updatewps_mod), 247	step_time_mod), 237
dtv (fortran variable in module updatewpt_mod), 250	dxidtlast_lmloc (fortran variable in module fieldslast),
dtv (fortran variable in module updatez_mod), 256	201
dtvpol2hint (fortran variable in module rms), 376	dz_lmloc (fortran variable in module fields), 200
dtvpollmr (fortran variable in module rms), 375	dz_rloc (fortran variable in module fields), 199
dtvrms() (fortran subroutine in module rms), 377	dzastrlmr (fortran variable in module tor-
dtvrms_file (fortran variable in module rms), 376	sional_oscillations), 391
dtvrmsl_sd (fortran variable in module rms), 375	dzastrlmr_rloc (fortran variable in module tor-
dtvrmsl_ta (fortran variable in module rms), 375	sional_oscillations), 391
dtvrmssd (fortran variable in module rms), 374	dzcorlmr (fortran variable in module tor-
dtvtor2hint (fortran variable in module rms), 374	sional_oscillations), 391
duhmeanr (fortran variable in module outpar_mod), 339	dzcorlmr_rloc (fortran variable in module tor-
dvpm (fortran variable in module outto_mod), 399	sional_oscillations), 391
dvpm_sloc (fortran variable in module outto_mod), 399	dzddvplmr (fortran variable in module tor-

sional_oscillations), 391	e_mag_cmb_l_sd (fortran variable in module spectra),
dzddvplmr_rloc (fortran variable in module tor-	345
sional_oscillations), 391	e_mag_cmb_m_ave (fortran variable in module spectra),
dzdt_lmloc (fortran variable in module step_time_mod),	346
237	e_mag_cmb_m_sd (fortran variable in module spectra),
dzdt_rloc (fortran variable in module step_time_mod),	346
237	e_mag_ic_file (fortran variable in module mag-
dzdtlast_lo (fortran variable in module fieldslast), 201	netic_energy), 328
dzdvplmr (fortran variable in module torsional_oscillations), 391	e_mag_oc_file (fortran variable in module mag- netic_energy), 328
dzdvplmr_rloc (fortran variable in module torsional_oscillations), 391	e_mag_p_l_ave (fortran variable in module spectra), 344 e_mag_p_l_sd (fortran variable in module spectra), 345
dzlflmr (fortran variable in module tor-	e_mag_p_m_ave (fortran variable in module spectra), 345
sional_oscillations), 391	e_mag_p_m_sd (fortran variable in module spectra), 345
dzlflmr_rloc (fortran variable in module tor-	e_mag_p_rl_ave (fortran variable in module spectra), 343
sional_oscillations), 391	345
dzrstrlmr (fortran variable in module torsional_oscillations), 391	e_mag_p_r_m_ave (fortran variable in module spectra), 346
dzrstrlmr_rloc (fortran variable in module torsional_oscillations), 391	e_mag_pmean (fortran variable in module output_mod), 323
dzs_global (fortran variable in module geos_mod), 403	e_mag_t_l_ave (fortran variable in module spectra), 344
dzstrlmr (fortran variable in module tor-	e_mag_t_l_sd (fortran variable in module spectra), 345
sional_oscillations), 391	e_mag_t_m_ave (fortran variable in module spectra), 345
dzstrlmr_rloc (fortran variable in module tor-	e_mag_t_m_sd (fortran variable in module spectra), 345
sional_oscillations), 391	e_mag_t_r_l_ave (fortran variable in module spectra),
dzvmean (fortran variable in module output_mod), 323	345
dzvplmr (fortran variable in module outto_mod), 399	e_mag_t_r_m_ave (fortran variable in module spectra),
dzvplmr_loc (fortran variable in module outto_mod), 398	345
E	e_mag_tmean (fortran variable in module output_mod), 323
e_dipa (fortran variable in module magnetic_energy), 328	e_p_asa (fortran variable in module kinetic_energy), 326
e_kin_file (fortran variable in module kinetic_energy),	e_p_asa (fortran variable in module magnetic_energy),
326	328
e_kin_p_l_ave (fortran variable in module spectra), 346	e_pa (fortran variable in module kinetic_energy), 326
e_kin_p_l_sd (fortran variable in module spectra), 346	e_pa (fortran variable in module magnetic_energy), 328
e_kin_p_m_ave (fortran variable in module spectra), 345	e_t_asa (fortran variable in module kinetic_energy), 326
e_kin_p_m_sd (fortran variable in module spectra), 345	e_t_asa (fortran variable in module magnetic_energy),
e_kin_p_r_l_ave (fortran variable in module spectra), 345	328
e_kin_p_r_m_ave (fortran variable in module spectra), 346	e_ta (fortran variable in module kinetic_energy), 326 e_ta (fortran variable in module magnetic_energy), 328
e_kin_pmean (fortran variable in module output_mod), 323	earth_compliance_file (fortran variable in module magnetic_energy), 328
e_kin_t_l_ave (fortran variable in module spectra), 346	ediffint (fortran variable in module power), 342
e_kin_t_l_sd (fortran variable in module spectra), 345	ek (fortran variable in module physical_parameters), 192
e_kin_t_m_ave (fortran variable in module spectra), 345	ekscaled (fortran variable in module physi-
e_kin_t_m_sd (fortran variable in module spectra), 345	cal_parameters), 189
e_kin_t_r_l_ave (fortran variable in module spectra), 345	elcmbmean (fortran variable in module output_mod), 323
e_kin_t_r_m_ave (fortran variable in module spectra), 345	elmean (fortran variable in module output_mod), 322 enscale (fortran variable in module num_param), 188
e_kin_tmean (fortran variable in module output_mod),	eparaximeanr (fortran variable in module outpar_mod),
322	339 anarmann (fortran variable in module outnor mod) 330
e_mag_cmb_l_ave (fortran variable in module spectra),	eparmeanr (fortran variable in module outpar_mod), 339
345	eperpaximeanr (fortran variable in module outpar_mod), 339

eperpmeanr (fortran variable in module outpar_mod), 339	fields_average() (fortran subroutine in module
eps (fortran variable in module geos_mod), 403 eps (fortran variable in module rms), 376	fields_average_mod), 372 fields_average_mod (module), 370
epsc (fortran variable in module physical_parameters),	fieldslast (module), 200
190	filehandle (fortran variable in module out_coeff), 368
epsc0 (fortran variable in module physical_parameters), 192	filehandle (fortran variable in module radial_spectra), 401 final_wait_array (fortran variable in module communica-
epscprof (fortran variable in module radial_functions), 231	tions), 213 finalize() (fortran subroutine in module co-
epscxi (fortran variable in module physical_parameters), 191	sine_transform_even), 286 finalize() (fortran subroutine in module co-
epscxi0 (fortran variable in module physical_parameters), 192	sine_transform_odd), 284 finalize() (fortran subroutine in module dtb_arrays_mod),
epss (fortran variable in module physical_parameters), 193	387 finalize() (fortran subroutine in module leg_helper_mod),
equat() (magic.cyl.Cyl method), 165	290
equat() (magic.MagicPotential method), 154	finalize() (fortran subroutine in module nonlin-
equat() (magic.Surf method), 144	ear_lm_mod), 279
equatContour() (in module magic.plotlib), 171 escale (fortran variable in module num_param), 188	finalize() (fortran subroutine in module to_arrays_mod), 396
etot (fortran variable in module output_mod), 322	finalize_blocking() (fortran subroutine in module block-
etotold (fortran variable in module output_mod), 322	ing), 316
expo_imp (fortran variable in module special), 208 ExtraPot (class in magic.potExtra), 161	finalize_coeffs() (fortran subroutine in module out_coeff), 368
F	finalize_communications() (fortran subroutine in module communications), 214
fac_loop (fortran variable in module special), 208	finalize_der_arrays() (fortran subroutine in module ra-
factorise() (fortran subroutine in module useful), 424	dial_der), 307
fast_read() (in module magic.libmagic), 174	finalize_dtb_mod() (fortran subroutine in module
fcondmeanr (fortran variable in module outpar_mod), 339	dtb_mod), 384 finalize_fft() (fortran subroutine in module fft), 300
fconvmeanr (fortran variable in module outpar_mod), 339	finalize_fields() (fortran subroutine in module fields), 200
fd_order (fortran variable in module truncation), 185 fd_order_bound (fortran variable in module truncation), 185	finalize_fields_average_mod() (fortran subroutine in module fields_average_mod), 372
fd_ratio (fortran variable in module truncation), 185	finalize_fieldslast() (fortran subroutine in module field-
fd_stretch (fortran variable in module truncation), 186	slast), 201
fft (module), 299	finalize_geos_mod() (fortran subroutine in module geos_mod), 404
fft() (magic.coeff.MagicCoeffR method), 151 fft99ajw() (fortran subroutine in module fft), 302	finalize_grenoble() (fortran subroutine in module special),
fft99bjw() (fortran subroutine in module fft), 302	209
fft_fac_complex() (fortran subroutine in module	finalize_horizontal_data() (fortran subroutine in module
fft_fac_mod), 287	horizontal_data), 235
fft_fac_mod (module), 287	finalize_init_fields() (fortran subroutine in module init_fields), 224
fft_fac_real() (fortran subroutine in module fft_fac_mod), 287	finalize_kinetic_energy() (fortran subroutine in module
fft_thetab() (fortran subroutine in module fft), 300	kinetic_energy), 326
fft_to_real() (fortran subroutine in module fft), 300	finalize_lmloop() (fortran subroutine in module lm-
fftjw() (fortran subroutine in module fft), 300	loop_mod), 244 finalize_magnetic_energy() (fortran subroutine in module
field_lmloc_container (fortran variable in module fields), 199	magnetic_energy), 329
field_rloc_container (fortran variable in module fields), 199	finalize_memory_counter() (fortran subroutine in module mem_alloc), 427
fields (module), 198	finalize_movie_data() (fortran subroutine in module movie_data), 353

- num param), 189
- finalize outmisc mod() (fortran subroutine in module outmisc mod), 333
- finalize outpar mod() (fortran subroutine in module outpar mod), 339
- finalize output() (fortran subroutine in module output mod), 323
- finalize_output_power() (fortran subroutine in module power), 342
- finalize_outrot() (fortran subroutine in module outrot), 335
- finalize outto mod() (fortran subroutine in module outto mod), 399
- finalize_probes() (fortran subroutine module probe_mod), 414
- finalize_radial_functions() (fortran subroutine in module radial functions), 231
- finalize radialloop() (fortran subroutine in module radialloop), 267
- finalize_riterthetablocking_openmp() (fortran subroutine in module riterthetablocking openmp mod), 274
- finalize rms() (fortran subroutine in module rms), 376 finalize spectra() (fortran subroutine in module spectra),
- finalize_step_time() (fortran subroutine in module step_time_mod), 238
- finalize_to() (fortran subroutine in module torsional oscillations), 392
- finalize_updateb() (fortran subroutine in module updateb_mod), 265
- finalize_updates() (fortran subroutine in module updates_mod), 259
- finalize updatewp() (fortran subroutine in module updatewp mod), 253
- finalize updatewps() (fortran subroutine in module updatewps_mod), 247
- finalize_updatewpt() (fortran subroutine in module updatewpt_mod), 250
- finalize updatexi() (fortran subroutine in module updatexi mod), 262
- finalize updatez() (fortran subroutine in module updatez_mod), 256
- fkinmeanr (fortran variable in module outpar_mod), 339 flow_lmloc_container (fortran variable in module fields),
- flow_rloc_container (fortran variable in module fields),
- four (fortran variable in module constants), 206 fourier2D() (magic.Butterfly method), 169
- fpoynmeanr (fortran variable in module outpar_mod), 339
- frames (fortran variable in module movie data), 352
- fresmeanr (fortran variable in module outpar mod), 339

finalize num param() (fortran subroutine in module fviscmeanr (fortran variable in module outpar mod), 339

- g0 (fortran variable in module physical_parameters), 190 g1 (fortran variable in module physical_parameters), 190 g2 (fortran variable in module physical_parameters), 190 gather_all_from_lo_to_rank0() (fortran subroutine in module communications), 215
- gather_from_lo_to_rank0() (fortran subroutine in module communications), 215
- gauleg() (fortran subroutine in module horizontal data),
- gauss (fortran variable in module horizontal data), 234 general_arrays_mod (module), 277
- geo2hint (fortran variable in module rms), 374
- geormsl sd (fortran variable in module rms), 375
- geormsl ta (fortran variable in module rms), 375
- geormssd (fortran variable in module rms), 376
- geos_file (fortran variable in module geos_mod), 403 geos_mod (module), 402
- geosmean (fortran variable in module output_mod), 322 get amplitude() (fortran subroutine in module spectra),
- get_angular_moment() (fortran subroutine in module outrot), 337
- get_b_nl_bcs() (fortran subroutine in module nonlinear bcs), 281
- get_b_surface() (fortran subroutine in module out movie), 365
- get_bmat() (fortran subroutine in module updateb_mod),
- get_bpol() (fortran subroutine in module out dtb frame). 389
- get_br_skew() (fortran subroutine in module magnetic_energy), 330
- get_br_v_bcs() (fortran subroutine in module nonlinear_bcs), **280**
- get_btor() (fortran subroutine in module out_dtb_frame),
- get_chebs_even() (fortran subroutine in module chebyshev_polynoms_mod), 282
- get_dcheb (fortran variable in module radial_der), 306
- get_dcheb_complex() (fortran subroutine in module radial der), 307
- get dcheb even() (fortran subroutine in module radial der even), 312
- get_dcheb_real_1d() (fortran subroutine in module radial der), 307
- get_ddcheb() (fortran subroutine in module radial_der), 307
- get_ddcheb_even() (fortran subroutine in module radial_der_even), 312
- get_dddcheb() (fortran subroutine in module radial_der), 308

- get_dddr() (fortran subroutine in module radial_der), 309 get_ddr() (fortran subroutine in module radial_der), 309 get_ddr_even() (fortran subroutine in module radial_der_even), 310
- get_ddrns_even() (fortran subroutine in module radial_der_even), 311
- get_dh_dtblm() (fortran subroutine in module dtb_mod), 385
- get_dr (fortran variable in module radial_der), 306
- get_dr_real_1d() (fortran subroutine in module radial_der), 308
- get_drns_even() (fortran subroutine in module radial_der_even), 311
- get_dtb() (fortran subroutine in module out_dtb_frame), 388
- get_dtblm() (fortran subroutine in module dtb_mod), 384 get_dtblmfinish() (fortran subroutine in module dtb_mod), 386
- get_e_kin() (fortran subroutine in module ki netic_energy), 326
- get_e_mag() (fortran subroutine in module magnetic_energy), 329
- get_fl() (fortran subroutine in module out_movie), 365
- get_fluxes() (fortran subroutine in module nl_special_calc), 411
- get_global_sum (fortran variable in module communications), 213

- get_helicity() (fortran subroutine in module nl_special_calc), 412
- get_hit_times() (fortran subroutine in module precalculations), 228
- get_lorder_lm_blocking() (fortran subroutine in module blocking), 316
- get_lorentz_torque() (fortran subroutine in module outrot), 336
- get_mean_sd (fortran variable in module useful), 423
- get_mean_sd_scalar() (fortran subroutine in module useful), 425
- get_mean_sd_vector() (fortran subroutine in module useful), 425
- get_movie_type() (fortran subroutine in module movie_data), 353
- get_p0mat() (fortran subroutine in module updatewp_mod), 254

- get_perppar() (fortran subroutine in module nl_special_calc), 410
- get_poltorrms() (fortran subroutine in module rms_helpers), 378
- get_power() (fortran subroutine in module power), 342 get_ps0mat() (fortran subroutine in module updatewps_mod), 248
- get_pt0mat() (fortran subroutine in module updatewpt_mod), 251
- get_sl() (fortran subroutine in module out_movie), 365 get_smat() (fortran subroutine in module updates_mod), 260
- $\begin{tabular}{ll} get_standard_lm_blocking() & (fortran subroutine in module blocking), 316 \\ \end{tabular}$
- $\begin{tabular}{ll} \tt get_subblocks() & (fortran subroutine in module blocking), \\ & 316 \end{tabular}$
- get_td() (fortran subroutine in module nonlinear_lm_mod), 279
- get_theta_blocking (fortran variable in module blocking), 315
- get_theta_blocking_openmp() (fortran subroutine in module blocking), 317

- get_viscous_torque (fortran variable in module outrot), 335
- $\begin{tabular}{ll} \tt get_viscous_torque_complex() & (fortran subroutine in module outrot), 336 \\ \end{tabular}$
- $\begin{tabular}{ll} \tt get_viscous_torque_real() & (fortran subroutine in module \\ \tt outrot), 336 \end{tabular}$
- get_wmat() (fortran subroutine in module updatewp_mod), 254
- get_wpmat() (fortran subroutine in module updatewp_mod), 254
- get_wptmat() (fortran subroutine in module updatewpt_mod), 251
- get_ximat() (fortran subroutine in module updatexi_mod), 263

<pre>get_z10mat() (fortran subroutine in module up- datez_mod), 257</pre>	gt_cheb (fortran variable in module communications), 214
get_zmat() (fortran subroutine in module updatez_mod), 258	gt_ic (fortran variable in module communications), 213 gt_oc (fortran variable in module communications), 213
getAccuratePeaks() (in module magic.bLayers), 162	
getastr() (fortran subroutine in module to_helpers), 395	Н
getbackground() (fortran subroutine in module ra-	half (fortran variable in module constants), 207
dial_functions), 232	hammer2cart() (in module magic.plotlib), 172
getCpuTime() (in module magic.libmagic), 175	hdif b (fortran variable in module horizontal data), 234
getdlm() (fortran subroutine in module getdlm_mod), 331	hdif_s (fortran variable in module horizontal_data), 234
getdlm_mod (module), 330	hdif_v (fortran variable in module horizontal_data), 234
getdvptr() (fortran subroutine in module geos_mod), 405	hdif_xi (fortran variable in module horizontal_data), 233
getegeos() (fortran subroutine in module geos_mod), 404	heat_file (fortran variable in module outmisc_mod), 332
getentropygradient() (fortran subroutine in module ra-	helicity_file (fortran variable in module outmisc_mod), 332
dial_functions), 232	•
getGauss() (in module magic.coeff), 152	332
getlm2lmo() (fortran subroutine in module readcheck-	hint2dpol() (fortran subroutine in module rms_helpers),
-	379
points), 418	hint2dpollm() (fortran subroutine in module
getMaxima() (in module magic.bLayers), 163	rms_helpers), 379
getpastr() (fortran subroutine in module to_helpers), 394	hint2pol() (fortran subroutine in module rms_helpers),
getstartfields() (fortran subroutine in module start_fields),	379
220	hint2pollm() (fortran subroutine in module rms_helpers),
getthistype() (fortran function in module riterthetablock-	380
ing_openmp_mod), 274	hint2tor() (fortran subroutine in module rms_helpers),
getto() (fortran subroutine in module tor-	381
sional_oscillations), 392	hint2torlm() (fortran subroutine in module rms_helpers),
gettofinish() (fortran subroutine in module tor-	381
sional_oscillations), 393	hintrms() (fortran subroutine in module rms_helpers), 380
gettonext() (fortran subroutine in module tor-	horizontal() (fortran subroutine in module horizon-
sional_oscillations), 393	tal_data), 235
getTotalRunTime() (in module magic.libmagic), 175	horizontal_data (module), 232
gradt2meanr (fortran variable in module outpar_mod),	human_readable_size() (fortran function in module
339	mem_alloc), 427
Graph2Vtk (class in magic.graph2vtk), 159	ww
graph_file (fortran variable in module output_data), 205	
graph_mpi_fh (fortran variable in module output_data),	i fft init (fortron variable in module fft) 300
204	i_fft_init (fortran variable in module fft), 300
graph_write() (fortran subroutine in module	ierr (fortran variable in module parallel_mod), 210
graphout_mod), 350	imageon (fortran variable in module physi-
graph_write_mpi() (fortran subroutine in module	cal_parameters), 193
graphout_mod), 351	imps (fortran variable in module physical_parameters),
graphout() (fortran subroutine in module graphout_mod),	191
349	impxi (fortran variable in module physical_parameters),
	192
U 1	inerp_file (fortran variable in module outrot), 335
graphout_mod), 349	inert_file (fortran variable in module outrot), 335
graphout_ic() (fortran subroutine in module	inform (fortran variable in module init_fields), 223
graphout_mod), 350	init_b1 (fortran variable in module init_fields), 222
graphout_mod (module), 348	init_fft() (fortran subroutine in module fft), 300
graphout_mpi() (fortran subroutine in module	init_fields (module), 221
graphout_mod), 349	init_rnb() (fortran subroutine in module rms), 377
graphout_mpi_header() (fortran subroutine in module	init_s1 (fortran variable in module init_fields), 223
graphout_mod), 350	init_s2 (fortran variable in module init_fields), 224
grunnb (fortran variable in module physical_parameters),	init_v1 (fortran variable in module init_fields), 223
192	init_xi1 (fortran variable in module init_fields), 223

- init_xi2 (fortran variable in module init_fields), 223 initb() (fortran subroutine in module init_fields), 225
- initialize() (fortran subroutine in module cosine_transform_even), 286
- initialize() (fortran subroutine in module cosine_transform_odd), 284
- initialize() (fortran subroutine in module dtb_arrays_mod), 387
- initialize() (fortran subroutine in module leg_helper_mod), **290**
- initialize() (fortran subroutine in module nonlinear_lm_mod), 279
- initialize() (fortran subroutine in module to_arrays_mod), 396
- initialize_blocking() (fortran subroutine in module blocking), 316
- initialize_coeffs() (fortran subroutine in module out coeff), 368
- initialize_communications() (fortran subroutine in module communications), 214
- initialize_der_arrays() (fortran subroutine in module radial der), 306
- initialize_dtb_mod() (fortran subroutine in module dtb mod), 384
- initialize_fields() (fortran subroutine in module fields), 200
- initialize_fields_average_mod() (fortran subroutine in module fields_average_mod), 372
- initialize_fieldslast() (fortran subroutine in module field-slast), **201**
- initialize_geos_mod() (fortran subroutine in module geos_mod), 404
- initialize_grenoble() (fortran subroutine in module special), 209
- initialize_horizontal_data() (fortran subroutine in module horizontal_data), 235
- initialize_kinetic_energy() (fortran subroutine in module kinetic_energy), 326
- initialize_lmloop() (fortran subroutine in module lm-loop_mod), 244
- initialize_lmloop_data() (fortran subroutine in module lmloop_data), 212
- initialize_magnetic_energy() (fortran subroutine in module magnetic_energy), **329**
- initialize_memory_counter() (fortran subroutine in module mem_alloc), 427
- initialize_movie_data() (fortran subroutine in module movie_data), 353
- initialize_num_param() (fortran subroutine in module num_param), 189
- initialize_outmisc_mod() (fortran subroutine in module outmisc mod), 333

- initialize_outpar_mod() (fortran subroutine in module outpar mod), 339
- initialize_output() (fortran subroutine in module output_mod), 323
- initialize_output_power() (fortran subroutine in module power), 342
- initialize_outrot() (fortran subroutine in module outrot), 335
- initialize_outto_mod() (fortran subroutine in module outto_mod), 399
- initialize_probes() (fortran subroutine in module probe_mod), 414
- initialize_radial_data() (fortran subroutine in module radial_data), **211**
- initialize_radial_functions() (fortran subroutine in module radial_functions), 231
- initialize_radialloop() (fortran subroutine in module radialloop), **267**
- initialize_riterthetablocking_openmp() (fortran subroutine in module riterthetablocking_openmp_mod), 274
- initialize_rms() (fortran subroutine in module rms), 376 initialize_spectra() (fortran subroutine in module spectra), 346
- initialize_step_time() (fortran subroutine in module step time mod), 238
- initialize_to() (fortran subroutine in module torsional_oscillations), 392
- initialize_truncation() (fortran subroutine in module truncation), 186
- initialize_updateb() (fortran subroutine in module updateb mod), 265
- initialize_updates() (fortran subroutine in module updates_mod), 259
- initialize_updatewp() (fortran subroutine in module updatewp_mod), 253
- initialize_updatewps() (fortran subroutine in module updatewps_mod), **247**
- $\begin{array}{c} \text{initialize_updatewpt() (fortran subroutine in module updatewpt_mod), } \textbf{250} \end{array}$
- initialize_updatexi() (fortran subroutine in module updatexi_mod), 262
- initialize_updatez() (fortran subroutine in module updatez_mod), 256
- inits() (fortran subroutine in module init_fields), 224
- inity() (fortran subroutine in module init_fields), 224
- initxi() (fortran subroutine in module init_fields), 225
- intcheb() (in module magic.libmagic), 175
- integBotTop() (in module magic.bLayers), 163
- integBulkBc() (in module magic.bLayers), 163
- integration (module), 313
- interior_model (fortran variable in module physical parameters), 191
- intfac (fortran variable in module num param), 188

istop (fortran variable in module num_param), 188	l_corrmov (fortran variable in module logic), 196
J	1_cour_alf_damp (fortran variable in module logic), 195
j_cond() (fortran subroutine in module init_fields), 225 jmat (fortran variable in module updateb_mod), 265 jmat_fac (fortran variable in module updateb_mod), 264 jpivot (fortran variable in module updateb_mod), 264 jvarcon (fortran variable in module radial_functions), 230	l_curr (fortran variable in module special), 208 l_diff_prec (fortran variable in module logic), 197 l_double_curl (fortran variable in module logic), 196 l_drift (fortran variable in module logic), 195 l_dt_cmb_field (fortran variable in module logic), 195 l_dtb (fortran variable in module logic), 197 l_dtbmovie (fortran variable in module logic), 194
K	l_dtrmagspec (fortran variable in module logic), 194
kappa (fortran variable in module radial_functions), 231 kbotb (fortran variable in module physical_parameters), 191	l_earth_likeness (fortran variable in module logic), 196 l_energy_modes (fortran variable in module logic), 197 l_finite_diff (fortran variable in module logic), 196 l_fluxprofs (fortran variable in module logic), 196
kbots (fortran variable in module physical_parameters), 190	l_graph_time (fortran variable in module output_data)
kbotv (fortran variable in module physical_parameters),	203 1_heat (fortran variable in module logic), 194
192 kbotxi (fortran variable in module physical_parameters),	l_heat_nl (fortran variable in module logic), 197
190	l_hel (fortran variable in module logic), 196
kinetic_energy (module), 325	l_ht (fortran variable in module logic), 197
ktopb (fortran variable in module physical_parameters), 189	1_htmovie (fortran variable in module logic), 196 1_imp (fortran variable in module special), 209
ktopp (fortran variable in module physical_parameters),	l_iner (fortran variable in module logic), 197 l_isothermal (fortran variable in module logic), 195
190	l_lcr (fortran variable in module logic), 194
ktops (fortran variable in module physical_parameters), 190	l_mag (fortran variable in module logic), 194
ktopv (fortran variable in module physical_parameters),	l_mag_kin (fortran variable in module logic), 197 l_mag_lf (fortran variable in module logic), 194
190	l_mag_nl (fortran variable in module logic), 195
ktopxi (fortran variable in module physical_parameters), 190	l_max (fortran variable in module truncation), 184
170	l_max_cmb (fortran variable in module output_data), 203
L	l_max_comp (fortran variable in module output_data)
l2lmas (fortran variable in module blocking), 316 l_2d_spectra (fortran variable in module logic), 195	203 l_max_r (fortran variable in module output_data), 205 l_maxmag (fortran variable in module truncation), 186
l_ab1 (fortran variable in module logic), 194	l_movie (fortran variable in module logic), 196
l_am (fortran variable in module logic), 195	l_movie_ic (fortran variable in module logic), 195
l_anel (fortran variable in module logic), 196	l_movie_oc (fortran variable in module logic), 196
l_anelastic_liquid (fortran variable in module logic), 196 l_average (fortran variable in module logic), 194	l_newmap (fortran variable in module logic), 196
l_axi (fortran variable in module truncation), 184	l_non_adia (fortran variable in module logic), 195
l_axi_old (fortran variable in module readcheckpoints),	l_non_rot (fortran variable in module logic), 194
416	l_par (fortran variable in module logic), 197
l_b_nl_cmb (fortran variable in module logic), 197	l_perppar (fortran variable in module logic), 194
l_b_nl_icb (fortran variable in module logic), 196	l_power (fortran variable in module logic), 197
l_chemical_conv (fortran variable in module logic), 195	l_precession (fortran variable in module logic), 197
l_cmb_field (fortran variable in module logic), 197	l_pressgraph (fortran variable in module logic), 195
l_cond_ic (fortran variable in module logic), 195	l_probe (fortran variable in module logic), 196
l_cond_ma (fortran variable in module logic), 196	l_pv (fortran variable in module logic), 194
l_conv (fortran variable in module logic), 195	l_r_field (fortran variable in module logic), 197
l_conv_nl (fortran variable in module logic), 196	l_r_fieldt (fortran variable in module logic), 194
l_corr (fortran variable in module logic), 197	l_reset_t (fortran variable in module init_fields), 222 l_ri (fortran variable in module special), 208
l_correct_ame (fortran variable in module logic), 194	l_rmagspec (fortran variable in module logic), 195
l_correct_amz (fortran variable in module logic), 194	l_rms (fortran variable in module logic), 197
1_correct_step() (fortran function in module useful), 423	

l_rot_ic (fortran variable in module logic), 196	legtfas() (fortran subroutine in module legen-
l_rot_ma (fortran variable in module logic), 197	dre_grid_to_spec), 298
l_runtimelimit (fortran variable in module logic), 196	legtfas2() (fortran subroutine in module legen-
l_save_out (fortran variable in module logic), 196	dre_grid_to_spec), 299
l_single_matrix (fortran variable in module logic), 195	legtfg() (fortran subroutine in module legen-
l_sric (fortran variable in module logic), 194	dre_spec_to_grid), 293
l_srma (fortran variable in module logic), 194	legtfgnomag() (fortran subroutine in module legen-
l_start_file (fortran variable in module init_fields), 223	dre_spec_to_grid), 294
l_store_frame (fortran variable in module logic), 197	length_to_blank() (fortran function in module charma-
l_storebpot (fortran variable in module logic), 195	nip), 428
l_storepot (fortran variable in module logic), 197	length_to_char() (fortran function in module charmanip),
l_storetpot (fortran variable in module logic), 196	428
l_storevpot (fortran variable in module logic), 195	lf2hint (fortran variable in module rms), 375
l_temperature_diff (fortran variable in module logic), 197	lffac (fortran variable in module physical_parameters),
l_time_hits (fortran variable in module logic), 194	192
l_to (fortran variable in module logic), 194	lfm (fortran variable in module outto_mod), 398
l_tomovie (fortran variable in module logic), 197	lfm_sloc (fortran variable in module outto_mod), 398
l_tp_form (fortran variable in module logic), 197	lfrmsl_sd (fortran variable in module rms), 375
l_true_time (fortran variable in module logic), 195	lfrmsl_ta (fortran variable in module rms), 376
l_update_b (fortran variable in module logic), 194	lfrmssd (fortran variable in module rms), 375
l_update_s (fortran variable in module logic), 195	lgrenoble (fortran variable in module special), 208
l_update_v (fortran variable in module logic), 194	licfield (fortran variable in module movie_data), 352
l_update_xi (fortran variable in module logic), 196	lip (fortran variable in module precision_mod), 183
l_visebecale (fortran variable in module logic), 195	llm (fortran variable in module lmloop_data), 211
l_z10mat (fortran variable in module logic), 195	llmmag (fortran variable in module lmloop_data), 211
lambda (fortran variable in module radial_functions), 231	lm2 (fortran variable in module blocking), 315
lbdissmean (fortran variable in module output_mod), 322	lm221 (fortran variable in module blocking), 315
lbmat (fortran variable in module updateb_mod), 264	lm22lm (fortran variable in module blocking), 316
ldif (fortran variable in module num_param), 188	lm22m (fortran variable in module blocking), 315
ldifexp (fortran variable in module num_param), 187	lm2l (fortran variable in module blocking), 315
ldtbmem (fortran variable in module truncation), 185	lm2lma (fortran variable in module blocking), 316
leg_helper_mod (module), 289	lm2lmp (fortran variable in module blocking), 315
leg_scal_to_grad_spat() (fortran subroutine in module	lm2lms (fortran variable in module blocking), 315
legendre_spec_to_grid), 296	lm2lo_redist() (fortran subroutine in module communica-
leg_scal_to_spat() (fortran subroutine in module legen-	tions), 217
dre_spec_to_grid), 296 legendre_grid_to_spec (module), 297	lm2m (fortran variable in module blocking), 315 lm2mc (fortran variable in module blocking), 315
legendre_spec_to_grid (module), 292	lm2pt() (fortran subroutine in module out_dtb_frame),
legprep() (fortran subroutine in module leg_helper_mod),	390
291	lm2r_redist_start() (fortran subroutine in module commu-
legprep_ic() (fortran subroutine in module	nications), 216
leg_helper_mod), 291	lm2r_redist_wait() (fortran subroutine in module commu-
legprepg() (fortran subroutine in module	nications), 216
leg_helper_mod), 290	lm_max (fortran variable in module truncation), 185
legtf() (fortran subroutine in module legen-	lm_max_comp (fortran variable in module mag-
dre_spec_to_grid), 295	netic_energy), 329
legtf1() (fortran subroutine in module legen-	lm_max_dtb (fortran variable in module truncation), 186
dre_grid_to_spec), 297	lm_max_real (fortran variable in module truncation), 186
legtf2() (fortran subroutine in module legen-	lm_maxmag (fortran variable in module truncation), 185
dre_grid_to_spec), 297	lm_on_last_rank (fortran variable in module lm-
legtf3() (fortran subroutine in module legen-	loop_data), 211
dre_grid_to_spec), 298	lm_per_rank (fortran variable in module lmloop_data),
legtf_spher_tor() (fortran subroutine in module legen-	211
dre_grid_to_spec), 298	lmagmem (fortran variable in module truncation), 185

<pre>lmas2pt() (fortran subroutine in module legen- dre_spec_to_grid), 296</pre>	lvdissmean (fortran variable in module output_mod), 323 lverbose (fortran variable in module logic), 194
lmloop() (fortran subroutine in module lmloop_mod), 244	lwpmat (fortran variable in module updatewp_mod), 253
Imloop_data (module), 211	lwpsmat (fortran variable in module updatewps_mod),
Imloop_mod (module), 243	246
Immapping (module), 317	lwptmat (fortran variable in module updatewpt_mod), 249
lmodd (fortran variable in module horizontal_data), 234	lximat (fortran variable in module updatexi_mod), 262
lmoddp (fortran variable in module horizontal_data), 234	lz10mat (fortran variable in module updatez_mod), 256
lmoviemem (fortran variable in module truncation), 185	lzmat (fortran variable in module updatez_mod), 256
lmp2 (fortran variable in module blocking), 315 lmp2l (fortran variable in module blocking), 315	M
lmp2lm (fortran variable in module blocking), 315	
lmp2lmpa (fortran variable in module blocking), 315	m_max (fortran variable in module truncation), 185
lmp2lmps (fortran variable in module blocking), 315	m_max_modes (fortran variable in module output_data), 205
lmp_max (fortran variable in module truncation), 185	m_riicasym (fortran variable in module special), 208
lmp_max_dtb (fortran variable in module truncation), 185	m_riicsym (fortran variable in module special), 209
lmstartb (fortran variable in module blocking), 315	m_rimasym (fortran variable in module special), 208
lmstopb (fortran variable in module blocking), 316	m_rimasym (fortran variable in module special), 208
lnegtime() (fortran function in module timing), 242	mag2hint (fortran variable in module rms), 376
lnpas2tr() (fortran function in module omega), 409	magic (fortran program), 181
lo2lm_redist() (fortran subroutine in module communica-	magic.bLayers (module), 162
tions), 217	magic.coeff (module), 149
lo2r_field (fortran variable in module communications),	magic.cyl (module), 164
214	magic.graph2vtk (module), 159
lo2r_flow (fortran variable in module communications),	magic.libmagic (module), 173
214	magic.plotlib (module), 171
lo2r_redist_start() (fortran subroutine in module commu-	magic.potExtra (module), 161
nications), 216	magic.spectralTransforms (module), 169
lo2r_redist_wait() (fortran subroutine in module commu-	MagicCoeffCmb (class in magic.coeff), 149
nications), 216	MagicCoeffR (class in magic.coeff), 151
lo2r_s (fortran variable in module communications), 214	MagicGraph (class in magic), 142
lo2r_xi (fortran variable in module communications), 214	MagicPotential (class in magic), 153
lo_map (fortran variable in module blocking), 315	MagicPV (class in magic), 157
lo_sub_map (fortran variable in module blocking), 315	MagicRadial (class in magic), 140
log_file (fortran variable in module output_data), 206	MagicRSpec (class in magic), 153
logic (module), 193	MagicSetup (class in magic), 138
logwrite() (fortran subroutine in module useful), 424	MagicSpectrum (class in magic), 140
lorentz_torque_iclast (fortran variable in module field-slast), 201	MagicSpectrum2D (class in magic), 141
lorentz_torque_malast (fortran variable in module field-	MagicTaySphere (class in magic), 157
slast), 201	MagicTOT (class in magic), 156
lp_file (fortran variable in module output_data), 205	MagicTOZ (class in magic), 156 MagicTs (class in magic), 138
lreadr (fortran variable in module readcheckpoints), 416	magnetic_energy (module), 327
lreads (fortran variable in module readcheckpoints), 416	magrmsl_sd (fortran variable in module rms), 375
lreadxi (fortran variable in module readcheckpoints), 416	magrmsl_ta (fortran variable in module rms), 376
lscale (fortran variable in module num_param), 188	magrmssd (fortran variable in module rms), 376
lsmat (fortran variable in module updates_mod), 259	map_function (fortran variable in module num_param),
lstart (fortran variable in module horizontal_data), 234	188
lstartp (fortran variable in module horizontal_data), 234	mapdatahydro() (fortran subroutine in module readcheck-
lstop (fortran variable in module horizontal_data), 234	points), 419
lstopp (fortran variable in module horizontal_data), 233	mapdatamag() (fortran subroutine in module readcheck-
lstoremov (fortran variable in module movie_data), 352	points), 419
lstressmem (fortran variable in module truncation), 184	mapdatar() (fortran subroutine in module readcheck-
ltimelimit() (fortran function in module timing), 242	points), 420

maponefield() (fortran subroutine in module readcheck-points), 418 mass (fortran variable in module constants), 207 matder() (in module magic.libmagic), 175 maxthreads (fortran variable in module updateb_mod),	msecminute (fortran variable in module timing), 241 msecsecond (fortran variable in module timing), 241 mvar (fortran variable in module outpar_mod), 339 myallgather() (fortran subroutine in module communications), 217
264 maxthreads (fortran variable in module updates_mod),	N
259 maxthreads (fortran variable in module updatewp_mod), 252	n_am_kpol_file (fortran variable in module spectra), 345 n_am_ktor_file (fortran variable in module spectra), 346 n_am_mpol_file (fortran variable in module spectra), 346
$max threads \ (for tran \ variable \ in \ module \ updatewps_mod), \\ {\color{red} \bf 246}$	n_am_mtor_file (fortran variable in module spectra), 345 n_angular_file (fortran variable in module outrot), 335
maxthreads (fortran variable in module updatewpt_mod), 249	n_b_r_file (fortran variable in module output_mod), 323 n_b_r_sets (fortran variable in module output_mod), 322
maxthreads (fortran variable in module updatexi_mod), 262	n_bpot_step (fortran variable in module output_data), 205 n_bpots (fortran variable in module output_data), 203
maxthreads (fortran variable in module updatez_mod), 256	n_calls (fortran variable in module power), 342 n_cheb_ic_max (fortran variable in module truncation),
meantime() (fortran subroutine in module timing), 242 mem_alloc (module), 426	184
memory_file (fortran variable in module mem_alloc), 427 memwrite() (fortran subroutine in module mem_alloc), 427	n_cheb_max (fortran variable in module truncation), 186 n_cheb_maxc (fortran variable in module rms), 375 n_cmb_file (fortran variable in module output_mod), 323 n_cmb_setsmov (fortran variable in module output_mod),
merContour() (in module magic.plotlib), 172	322
minc (fortran variable in module truncation), 184 mode (fortran variable in module physical_parameters), 191	n_cmb_step (fortran variable in module output_data), 203 n_cmbmov_file (fortran variable in module output_mod), 322
movfile (fortran variable in module outto_mod), 398	n_cmbs (fortran variable in module output_data), 204
Movie (class in magic), 146	n_coeff_r (fortran variable in module output_data), 205
movie (fortran variable in module movie_data), 352 Movie3D (class in magic), 148	n_coeff_r_max (fortran variable in module output_data), 205
movie_const (fortran variable in module movie_data), 352	n_compliance_file (fortran variable in module magnetic_energy), 328
movie_data (module), 351	n_cour_step (fortran variable in module num_param), 187
movie_file (fortran variable in module movie_data), 352 movie_gather_frames_to_rank0() (fortran subroutine in	n_dipole_file (fortran variable in module magnetic_energy), 328
module movie_data), 359	n_driftbd_file (fortran variable in module outrot), 335
movieCmb() (magic.coeff.MagicCoeffCmb method), 150 moviedipcolat (fortran variable in module movie_data),	n_driftbq_file (fortran variable in module outrot), 335
352	n_driftvd_file (fortran variable in module outrot), 335 n_driftvq_file (fortran variable in module outrot), 335
moviediplon (fortran variable in module movie_data), 352	n_dt_cmb_file (fortran variable in module output_mod),
moviedipstrength (fortran variable in module movie_data), 353	322 n_dt_cmb_sets (fortran variable in module output_mod),
moviedipstrengthgeo (fortran variable in module movie_data), 352	323 n_dtbrms_file (fortran variable in module rms), 376
movieRad() (magic.coeff.MagicCoeffR method), 151	n_dte_file (fortran variable in module output_mod), 322
mpi_def_complex (fortran variable in module precision_mod), 183	n_dtvrms_file (fortran variable in module rms), 375 n_e_kin_file (fortran variable in module kinetic_energy),
mpi_def_real (fortran variable in module precision_mod), 183	326
mpi_out_real (fortran variable in module precision_mod), 183	n_e_mag_ic_file (fortran variable in module mag- netic_energy), 328 n_e_mag_oc_file (fortran variable in module mag-
ms2time() (fortran subroutine in module timing), 241	netic_energy), 329
msechour (fortran variable in module timing), 241	n e sets (fortran variable in module output mod), 322

n frame work (fortran variable in module movie data), n geos file (fortran variable in module geos mod), 403 n graph file (fortran variable in module output data), n graph step (fortran variable in module output data), n graphs (fortran variable in module output data), 202 n heat file (fortran variable in module outmisc mod), n_helicity_file (fortran variable in module outmisc_mod), 332 n imp (fortran variable in module special), 209 n_imps (fortran variable in module physical_parameters), n_imps_max (fortran variable in module physical_parameters), 191 (fortran variable n impxi module physical parameters), 189 n impxi max (fortran variable in module physical parameters), 193 n inerp file (fortran variable in module outrot), 335 n_inert_file (fortran variable in module outrot), 335 n kin spec file (fortran variable in module spectra), 344 n log file (fortran variable in module output data), 204 n log step (fortran variable in module output data), 203 n_logs (fortran variable in module output_data), 205 n_lscale (fortran variable in module num_param), 187 n_m_max (fortran variable in module truncation), 185 n mag spec file (fortran variable in module spectra), 346 n_md (fortran variable in module movie_data), 352 n_memory_file (fortran variable in module mem_alloc), n_movie_const (fortran variable in module movie data), 352 n movie field start (fortran variable in module movie data), 352 n_movie_field_stop (fortran variable in module movie data), 352 n_movie_field_type (fortran variable module movie data), 352 n movie fields (fortran variable in module movie data), n_movie_fields_ic (fortran variable module in movie_data), 352 n_movie_fields_max (fortran variable module movie data), 352 n_movie_file (fortran variable in module movie_data), 352 n_movie_frames (fortran variable in module output_data), 204 n_movie_step (fortran variable in module output_data), 205 n movie surface (fortran variable

```
movie data), 352
         n movie type (fortran variable in module movie data),
         n_movies (fortran variable in module movie_data), 352
         n movies max (fortran variable in module movie data),
         n out probes (fortran variable in module probe mod),
         n par file (fortran variable in module output mod), 322
         n_perppar_file (fortran variable in module outpar_mod),
         n_phi_max (fortran variable in module truncation), 186
         n_phi_max_comp (fortran variable in module mag-
                   netic_energy), 328
         n_phi_maxstr (fortran variable in module truncation), 184
         n_phi_probes (fortran variable in module probe_mod),
         n phi tot (fortran variable in module truncation), 185
         n pot step (fortran variable in module output data), 205
         n pots (fortran variable in module output data), 204
         n_power_file (fortran variable in module power), 342
         n probe out (fortran variable in module output data),
         n_probe_step (fortran variable in module output data).
                   204
         n procs (fortran variable in module parallel mod), 210
         n_r_array (fortran variable in module output_data), 203
         n_r_cmb (fortran variable in module radial_data), 211
         n_r_field_step (fortran variable in module output_data),
         n_r_fields (fortran variable in module output_data), 205
         n_r_ic_max (fortran variable in module truncation), 184
         n_r_ic_max_dtb (fortran variable in module truncation),
         n r ic maxmag (fortran variable in module truncation),
         n r icb (fortran variable in module radial data), 211
         n r lcr (fortran variable in module physical parameters),
         n_r_max (fortran variable in module truncation), 185
         n r max dtb (fortran variable in module truncation), 186
         n r maxc (fortran variable in module rms), 376
         n r maxmag (fortran variable in module truncation). 184
         n_r_maxstr (fortran variable in module truncation), 186
         n_r_step (fortran variable in module output_data), 202
         n_r_tot (fortran variable in module truncation), 185
         n_r_totmag (fortran variable in module truncation), 186
         n_ranks_print (fortran variable in module mem_alloc),
                   427
         n_rot_file (fortran variable in module outrot), 335
         n_rst_step (fortran variable in module output_data), 204
         n rsts (fortran variable in module output data), 204
         n s bounds (fortran variable in module init fields), 222
module n spec (fortran variable in module output mod), 323
```

n_spec_step (fortran variable in module output_data), 205	n_v_r_sets (fortran variable in module output_mod), 322
n_specs (fortran variable in module output_data), 204	n_vpot_step (fortran variable in module output_data), 204
n_sric_file (fortran variable in module outrot), 335	n_vpots (fortran variable in module output_data), 204
n_srma_file (fortran variable in module outrot), 335	n_xi_bounds (fortran variable in module init_fields), 223
n_start_file (fortran variable in module readcheckpoints),	nalias (fortran variable in module truncation), 185
416	namelists (module), 218
n_stores (fortran variable in module output_data), 205	nbdown (fortran variable in module blocking), 316
n_t_bpot (fortran variable in module output_data), 203	nbpotsets (fortran variable in module output_mod), 321
n_t_cmb (fortran variable in module output_data), 202	nbsave (fortran variable in module blocking), 315
n_t_graph (fortran variable in module output_data), 204	ncp (fortran variable in module truncation), 185
n_t_log (fortran variable in module output_data), 205	ncut (fortran variable in module rms), 375
n_t_movie (fortran variable in module output_data), 204	nd (fortran variable in module fft), 300
n_t_pot (fortran variable in module output_data), 203	ndd_costf1 (fortran variable in module radial_functions),
n_t_probe (fortran variable in module output_data), 204	230
n_t_r_field (fortran variable in module output_data), 205	ndd_costf1_ic (fortran variable in module ra-
n_t_r_file (fortran variable in module output_mod), 322	dial_functions), 231
n_t_r_sets (fortran variable in module output_mod), 322	
· · · · · · · · · · · · · · · · · · ·	ndd_costf2_ic (fortran variable in module ra- dial functions), 231
n_t_rst (fortran variable in module output_data), 205	-
n_t_spec (fortran variable in module output_data), 202	`
n_t_to (fortran variable in module output_data), 204	dial_functions), 231
n_t_tomovie (fortran variable in module output_data),	ndi_costf2_ic (fortran variable in module ra-
203	dial_functions), 230
n_t_toz (fortran variable in module output_data), 202	nfs (fortran variable in module blocking), 316
n_t_tpot (fortran variable in module output_data), 205	ni (fortran variable in module fft), 300
n_t_vpot (fortran variable in module output_data), 205	nl_special_calc (module), 409
n_temp_spec_file (fortran variable in module spectra), 346	nlmbs (fortran variable in module blocking), 315 nlmbs2 (fortran variable in module blocking), 315
n_theta_axi (fortran variable in module truncation), 185	nlmbs_per_rank (fortran variable in module paral-
n_theta_cal2ord (fortran variable in module horizon-	lel_mod), 210
tal_data), 234	nlogs (fortran variable in module output_mod), 322
n_theta_max (fortran variable in module truncation), 184	nonlinear_bcs (module), 280
n_theta_max_comp (fortran variable in module mag-	nonlinear_lm_mod (module), 277
netic_energy), 328	npvsets (fortran variable in module output_mod), 322
n_theta_maxstr (fortran variable in module truncation),	nr_on_last_rank (fortran variable in module paral-
185	lel_mod), 210
n_theta_usr (fortran variable in module probe_mod), 414	nr_per_rank (fortran variable in module parallel_mod),
n_time_hits (fortran variable in module output_data), 203	210
`	nrms_sets (fortran variable in module output_mod), 323
n_time_steps (fortran variable in module num_param), 187	nrotic (fortran variable in module init_fields), 224
n_to_step (fortran variable in module output_data), 203	nrotma (fortran variable in module init_fields), 223
n_tomovie_frames (fortran variable in module out-	nrp (fortran variable in module truncation), 185
put_data), 204	nrstart (fortran variable in module radial_data), 211
n_tomovie_step (fortran variable in module output_data),	nrstartmag (fortran variable in module radial_data), 211
204	nrstop (fortran variable in module radial_data), 211
n_tos (fortran variable in module output_data), 204	nrstopmag (fortran variable in module radial_data), 211
n_toz_step (fortran variable in module output_data), 205	ns_on_last_rank (fortran variable in module geos_mod),
n_tozs (fortran variable in module output_data), 202	403
n_tpot_step (fortran variable in module output_data), 202	ns_on_last_rank (fortran variable in module outto_mod),
n_tpots (fortran variable in module output_data), 202	398
n_tscale (fortran variable in module num_param), 188	ns_per_rank (fortran variable in module geos_mod), 403
n_u2_spec_file (fortran variable in module spectra), 345	ns_per_rank (fortran variable in module outto_mod), 398
n_u_square_file (fortran variable in module ki-	nsmax (fortran variable in module geos_mod), 403
netic_energy), 326	nsmax (fortran variable in module omega), 408
n v r file (fortran variable in module output mod) 322	nsmax (fortran variable in module outto, mod) 399

nsstart (fortran variable in module geos_mod), 403 nsstart (fortran variable in module outto_mod), 399 nsstop (fortran variable in module geos_mod), 403 nsstop (fortran variable in module geos_mod), 403 nsstop (fortran variable in module blocking), 315 nthreads (fortran variable in module parallel_mod), 210 ntomovsets (fortran variable in module output_mod), 322 ntormssets (fortran variable in module output_mod), 322 ntozfile (fortran variable in module output_mod), 322 ntozfile (fortran variable in module output_mod), 322 num_param (module), 186 nvarcond (fortran variable in module output_mod), 322 num_parameters), 193 nvardiff (fortran variable in module physical_parameters), 192 nvarentropygrad (fortran variable in module physical_parameters), 190 nvareps (fortran variable in module physical_parameters), 191 nvarvisc (fortran variable in module physical_parameters), 191 nvpotsets (fortran variable in module output_mod), 323 nz2 (fortran variable in module geos_mod), 403 nzc (fortran variable in module geos_mod), 403 nzc_sloc (fortran variable in module geos_mod), 403 nzmaxa (fortran variable in module geos_mod), 403 nzmaxa (fortran variable in module outto_mod), 398	omega_ma2 (fortran variable in module init_fields), 223 omega_riicasym (fortran variable in module special), 208 omega_riicsym (fortran variable in module special), 208 omega_rimaasym (fortran variable in module special), 209 omega_rimasym (fortran variable in module special), 209 omegaosz_ic1 (fortran variable in module init_fields), 222 omegaosz_ic2 (fortran variable in module init_fields), 222 omegaosz_ma1 (fortran variable in module init_fields), 224 omegaosz_ma2 (fortran variable in module init_fields), 224 one (fortran variable in module constants), 206 opm (fortran variable in module physical_parameters), 191 opr (fortran variable in module radial_functions), 230 or1 (fortran variable in module radial_functions), 230 or3 (fortran variable in module radial_functions), 230 or4 (fortran variable in module radial_functions), 231 orbo1 (fortran variable in module radial_functions), 231 orbo2 (fortran variable in module physical_parameters), 190 osints (fortran variable in module physical_parameters), 190 osints (fortran variable in module geos_mod), 403 osints (fortran variable in module outto_mod), 398 osintspv (fortran variable in module horizontal_data), 233 osn1 (fortran variable in module horizontal_data), 233 osn2 (fortran variable in module horizontal_data), 233
nzmaxs (fortran variable in module geos_mod), 403 nzmaxs (fortran variable in module outto_mod), 398	osq4pi (fortran variable in module constants), 207 otemp1 (fortran variable in module radial_functions), 230
nzmaxs_sloc (fortran variable in module outto_mod), 398	out_coeff (module), 367 out_dtb_frame (module), 387
0	out_movie (module), 359 out_movie_ic (module), 366
o_r_ic (fortran variable in module radial_functions), 230 o_r_ic2 (fortran variable in module radial_functions), 231 o_sin_theta (fortran variable in module horizontal_data),	outheat() (fortran subroutine in module outmisc_mod), 333
o_sin_theta_e2 (fortran variable in module horizon-tal_data), 234	outhelicity() (fortran subroutine in module outmisc_mod), 333 outmisc_mod (module), 331
o_sr (fortran variable in module physical_parameters), 192	outomega() (fortran subroutine in module omega), 408 outp (fortran variable in module precision_mod), 183
oek (fortran variable in module physical_parameters), 193 ogrun (fortran variable in module radial_functions), 230 ohmdissr_mean (fortran variable in module power), 342 ohmdissr_sd (fortran variable in module power), 342	outpar() (fortran subroutine in module outpar_mod), 340 outpar_mod (module), 338 outperppar() (fortran subroutine in module outpar_mod), 340
ohmlossfac (fortran variable in module physical_parameters), 190	output() (fortran subroutine in module nonlinear_lm_mod), 279 output() (fortran subroutine in module output, mod), 323
omega (module), 408 omega_diff (fortran variable in module init_fields), 223 omega_ic (fortran variable in module fields), 200 omega_ic1 (fortran variable in module init_fields), 223 omega_ic2 (fortran variable in module init_fields), 223	output() (fortran subroutine in module output_mod), 323 output_data (module), 201 output_mod (module), 319 outpv() (fortran subroutine in module geos_mod), 404 outrot (module), 334
omega_ma (fortran variable in module fields), 199 omega_ma1 (fortran variable in module init_fields), 223	outto() (fortran subroutine in module outto_mod), 399

outto_allgather_rloc() (fortran subroutine in module outto_mod), 400	plot() (magic.bLayers.BLayers method), 162 plot() (magic.Butterfly method), 169
outto_mod (module), 396	plot() (magic.coeff.MagicCoeffCmb method), 150
P	plot() (magic.MagicPV method), 158 plot() (magic.MagicRadial method), 140
p0mat (fortran variable in module updatewp_mod), 253	plot() (magic.MagicSpectrum method), 141
p0pivot (fortran variable in module updatewp_mod), 253	plot() (magic.MagicSpectrum2D method), 142
p_ave (fortran variable in module fields_average_mod),	plot() (magic.MagicTaySphere method), 157
371	plot() (magic.MagicTOHemi method), 157
p_ave_global (fortran variable in module	plot() (magic.MagicTs method), 139
fields_average_mod), 371	plot() (magic.Movie method), 148
p_lmloc (fortran variable in module fields), 199	plot() (magic.ThetaHeat method), 164
p_rloc (fortran variable in module fields), 199	plot() (magic.TOMovie method), 156
padvlm (fortran variable in module dtb_mod), 383	plotAvg() (magic.CompSims method), 159
padvlm_lmloc (fortran variable in module dtb_mod), 383	plotAvg() (magic.MagicRSpec method), 153
padvlm_rloc (fortran variable in module dtb_mod), 384	plotEmag() (magic.CompSims method), 159
padvlmic (fortran variable in module dtb_mod), 383	plotEquat() (magic.CompSims method), 159
padvlmic_lmloc (fortran variable in module dtb_mod),	plotFlux() (magic.CompSims method), 159
384	plotSurf() (magic.CompSims method), 159
par_file (fortran variable in module output_mod), 323	plotTs() (magic.CompSims method), 159
parallel() (fortran subroutine in module parallel_mod),	plotZonal() (magic.CompSims method), 159
210	pmeanr (fortran variable in module outmisc_mod), 332
parallel_mod (module), 209	po (fortran variable in module physical_parameters), 191
pdiffm (fortran variable in module dtb_mod), 384	po_diff (fortran variable in module physical_parameters),
pdiffm_lmloc (fortran variable in module dtb_mod), 383	191
pdiffmic (fortran variable in module dtb_mod), 383	polind (fortran variable in module physical_parameters),
pdiffmic_lmloc (fortran variable in module dtb_mod), 383	192
peaks (fortran variable in module physical_parameters), 193	polo_flow_eq (fortran variable in module num_param), 187
peakxi (fortran variable in module physical_parameters), 191	polynomial_interpolation() (fortran subroutine in module useful), 425
perppar_file (fortran variable in module outpar_mod), 339	polynomial_interpolation_real() (fortran subroutine in
phi (fortran variable in module horizontal_data), 234	module useful), 425
phideravg() (in module magic.libmagic), 176	polynomialbackground() (fortran subroutine in module
phis (fortran variable in module physical_parameters),	radial_functions), 232
193	
	power (module), 341
phixi (fortran variable in module physical_parameters),	power_file (fortran variable in module power), 342
phixi (fortran variable in module physical_parameters), 193	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189 pi (fortran variable in module constants), 207	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190 pre (fortran variable in module updatewp_mod), 252
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189 pi (fortran variable in module constants), 207 plf2hint (fortran variable in module rms), 376	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190 pre (fortran variable in module updatewp_mod), 252 pre (fortran variable in module updatewps_mod), 246
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189 pi (fortran variable in module constants), 207 plf2hint (fortran variable in module rms), 376 plfrmsl_sd (fortran variable in module rms), 374	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190 pre (fortran variable in module updatewp_mod), 252 pre (fortran variable in module updatewps_mod), 246 pre (fortran variable in module updatewpt_mod), 249
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189 pi (fortran variable in module constants), 207 plf2hint (fortran variable in module rms), 376 plfrmsl_sd (fortran variable in module rms), 374 plfrmsl_ta (fortran variable in module rms), 375	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190 pre (fortran variable in module updatewp_mod), 252 pre (fortran variable in module updatewps_mod), 246 pre (fortran variable in module updatewpt_mod), 249 pre2hint (fortran variable in module rms), 376
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189 pi (fortran variable in module constants), 207 plf2hint (fortran variable in module rms), 376 plfrmsl_sd (fortran variable in module rms), 374 plfrmsl_ta (fortran variable in module rms), 375 plfrmssd (fortran variable in module rms), 375	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190 pre (fortran variable in module updatewp_mod), 252 pre (fortran variable in module updatewps_mod), 246 pre (fortran variable in module updatewpt_mod), 249 pre2hint (fortran variable in module rms), 376 prec_angle (fortran variable in module physi-
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189 pi (fortran variable in module constants), 207 plf2hint (fortran variable in module rms), 376 plfrmsl_sd (fortran variable in module rms), 374 plfrmsl_ta (fortran variable in module rms), 375 plfrmssd (fortran variable in module rms), 375 plm (fortran variable in module horizontal_data), 234	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190 pre (fortran variable in module updatewp_mod), 252 pre (fortran variable in module updatewps_mod), 246 pre (fortran variable in module updatewpt_mod), 249 pre2hint (fortran variable in module rms), 376 prec_angle (fortran variable in module physical_parameters), 191
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189 pi (fortran variable in module constants), 207 plf2hint (fortran variable in module rms), 376 plfrmsl_sd (fortran variable in module rms), 374 plfrmsl_ta (fortran variable in module rms), 375 plfrmssd (fortran variable in module rms), 375 plm (fortran variable in module horizontal_data), 234 plm_comp (fortran variable in module magnetic_energy), 328	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190 pre (fortran variable in module updatewp_mod), 252 pre (fortran variable in module updatewps_mod), 246 pre (fortran variable in module updatewpt_mod), 249 pre2hint (fortran variable in module rms), 376 prec_angle (fortran variable in module physical_parameters), 191 precalc() (fortran subroutine in module precalculations), 227
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189 pi (fortran variable in module constants), 207 plf2hint (fortran variable in module rms), 376 plfrmsl_sd (fortran variable in module rms), 374 plfrmsl_ta (fortran variable in module rms), 375 plfrmssd (fortran variable in module rms), 375 plm (fortran variable in module horizontal_data), 234 plm_comp (fortran variable in module magnetic_energy),	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190 pre (fortran variable in module updatewp_mod), 252 pre (fortran variable in module updatewps_mod), 246 pre (fortran variable in module updatewpt_mod), 249 pre2hint (fortran variable in module rms), 376 prec_angle (fortran variable in module physical_parameters), 191 precalc() (fortran subroutine in module precalculations), 227 precalctimes() (fortran subroutine in module precalculations), 228
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189 pi (fortran variable in module constants), 207 plf2hint (fortran variable in module rms), 376 plfrmsl_sd (fortran variable in module rms), 374 plfrmsl_ta (fortran variable in module rms), 375 plfrmssd (fortran variable in module rms), 375 plm (fortran variable in module horizontal_data), 234 plm_comp (fortran variable in module magnetic_energy), 328 plm_theta() (fortran subroutine in module plms_theta),	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190 pre (fortran variable in module updatewp_mod), 252 pre (fortran variable in module updatewps_mod), 246 pre (fortran variable in module updatewpt_mod), 249 pre2hint (fortran variable in module rms), 376 prec_angle (fortran variable in module physical_parameters), 191 precalc() (fortran subroutine in module precalculations), 227 precalctimes() (fortran subroutine in module precalculations), 228 precalculations (module), 226
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189 pi (fortran variable in module constants), 207 plf2hint (fortran variable in module rms), 376 plfrmsl_sd (fortran variable in module rms), 374 plfrmsl_ta (fortran variable in module rms), 375 plfrmssd (fortran variable in module rms), 375 plm (fortran variable in module horizontal_data), 234 plm_comp (fortran variable in module magnetic_energy), 328 plm_theta() (fortran subroutine in module plms_theta), 288 plms (fortran variable in module geos_mod), 403 plms (fortran variable in module outto_mod), 398	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190 pre (fortran variable in module updatewp_mod), 252 pre (fortran variable in module updatewps_mod), 246 pre (fortran variable in module updatewpt_mod), 249 pre2hint (fortran variable in module rms), 376 prec_angle (fortran variable in module physical_parameters), 191 precalc() (fortran subroutine in module precalculations), 227 precalctimes() (fortran subroutine in module precalculations), 228 precalculations (module), 226 precision_mod (module), 183
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189 pi (fortran variable in module constants), 207 plf2hint (fortran variable in module rms), 376 plfrmsl_sd (fortran variable in module rms), 374 plfrmsl_ta (fortran variable in module rms), 375 plfrmssd (fortran variable in module rms), 375 plm (fortran variable in module horizontal_data), 234 plm_comp (fortran variable in module magnetic_energy), 328 plm_theta() (fortran subroutine in module plms_theta), 288 plms (fortran variable in module geos_mod), 403 plms (fortran variable in module outto_mod), 398 plms_theta (module), 288	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190 pre (fortran variable in module updatewp_mod), 252 pre (fortran variable in module updatewps_mod), 246 pre (fortran variable in module updatewpt_mod), 249 pre2hint (fortran variable in module rms), 376 prec_angle (fortran variable in module physical_parameters), 191 precalc() (fortran subroutine in module precalculations), 227 precalctimes() (fortran subroutine in module precalculations), 228 precalculations (module), 226 precision_mod (module), 183 prepare_mat() (fortran subroutine in module algebra), 305
phixi (fortran variable in module physical_parameters), 193 physical_parameters (module), 189 pi (fortran variable in module constants), 207 plf2hint (fortran variable in module rms), 376 plfrmsl_sd (fortran variable in module rms), 374 plfrmsl_ta (fortran variable in module rms), 375 plfrmssd (fortran variable in module rms), 375 plm (fortran variable in module horizontal_data), 234 plm_comp (fortran variable in module magnetic_energy), 328 plm_theta() (fortran subroutine in module plms_theta), 288 plms (fortran variable in module geos_mod), 403 plms (fortran variable in module outto_mod), 398	power_file (fortran variable in module power), 342 powerdiff (fortran variable in module power), 342 pr (fortran variable in module physical_parameters), 190 pre (fortran variable in module updatewp_mod), 252 pre (fortran variable in module updatewps_mod), 246 pre (fortran variable in module updatewpt_mod), 249 pre2hint (fortran variable in module rms), 376 prec_angle (fortran variable in module physical_parameters), 191 precalc() (fortran subroutine in module precalculations), 227 precalctimes() (fortran subroutine in module precalculations), 228 precalculations (module), 226 precision_mod (module), 183

prermssd (fortran variable in module rms), 375 prmag (fortran variable in module physical_parameters),	r_surface (fortran variable in module radial_functions), 230
191 probe_file (fortran variable in module probe_mod), 414	r_transfer_type (fortran variable in module communications), 213
probe_mod (module), 413	r_transfer_type_cont (fortran variable in module commu-
probe_out() (fortran subroutine in module probe_mod),	nications), 214
414	r_transfer_type_nr_end (fortran variable in module com-
progressbar() (in module magic.libmagic), 176	munications), 214
ps0mat (fortran variable in module updatewps_mod), 246 ps0mat_fac (fortran variable in module updatewps_mod),	r_transfer_type_nr_end_cont (fortran variable in module communications), 214
246	ra (fortran variable in module physical_parameters), 192
ps0pivot (fortran variable in module updatewps_mod), 246	rad_rank (fortran variable in module probe_mod), 414 rad_usr (fortran variable in module probe_mod), 414
ps_cond() (fortran subroutine in module init_fields), 226	radial() (fortran subroutine in module radial_functions),
pscale (fortran variable in module num_param), 188	232
pstrlm (fortran variable in module dtb_mod), 384	radial_data (module), 210
pstrlm_lmloc (fortran variable in module dtb_mod), 383	radial_der (module), 306
pstrlm_rloc (fortran variable in module dtb_mod), 384	radial_der_even (module), 310
pt0mat (fortran variable in module updatewpt_mod), 250	radial_functions (module), 229
pt0mat_fac (fortran variable in module updatewpt_mod), 250	radial_scheme (fortran variable in module truncation), 185
pt0pivot (fortran variable in module updatewpt_mod), 250	radial_spectra (module), 400
pt_cond() (fortran subroutine in module init_fields), 226	radialContour() (in module magic.plotlib), 172
R	radialloop (module), 266
	radialloopg() (fortran subroutine in module radialloop),
r (fortran variable in module radial_functions), 230	267
r2lm_redist_start() (fortran subroutine in module communications), 216	radratio (fortran variable in module physical_parameters), 190
r2lm_redist_wait() (fortran subroutine in module communications), 217	random() (fortran function in module useful), 423 rank_bn (fortran variable in module parallel_mod), 210
r2lo_b (fortran variable in module communications), 214 r2lo_dtb (fortran variable in module dtb_mod), 384	rank_with_11m0 (fortran variable in module parallel_mod), 210
r2lo_flow (fortran variable in module communications),	ranks_selected (fortran variable in module mem_alloc), 427
r2lo_redist_start() (fortran subroutine in module communications), 217	rascaled (fortran variable in module physical_parameters), 191
r2lo_redist_wait() (fortran subroutine in module communications), 217	raxi (fortran variable in module physical_parameters), 191
r2lo_s (fortran variable in module communications), 214 r2lo_xi (fortran variable in module communications), 213	rbpspec() (fortran subroutine in module radial_spectra), 401
r_cmb (fortran variable in module radial_functions), 231	rbrspec() (fortran subroutine in module radial_spectra),
r_cut_model (fortran variable in module physi-	401
cal_parameters), 193	rc (fortran variable in module rms), 376
r_ic (fortran variable in module radial_functions), 231	rcut (fortran variable in module output_data), 205
r_icb (fortran variable in module radial_functions), 231	rdea (fortran variable in module output_data), 206
r_lcr (fortran variable in module physical_parameters),	rderavg() (in module magic.libmagic), 176
191	readcheckpoints (module), 415
r_lm_gather_type (fortran variable in module communications), 213	readnamelists() (fortran subroutine in module namelists), 218
r_lm_gather_type_lm_end (fortran variable in module	readstartfields() (fortran subroutine in module readcheck-
communications), 214	points), 417
r_probe (fortran variable in module probe_mod), 414	readstartfields_old() (fortran subroutine in module read-
r_request (fortran variable in module communications),	checkpoints), 416
213	rearangeLat() (in module magic.coeff), 152

rearangeLat() (magic.MagicGraph method), 142 rgrav (fortran variable in module radial_functions), 230	s_request (fortran variable in module communications),
rho0 (fortran variable in module radial_functions), 230	s_rloc (fortran variable in module fields), 199
rho_ratio_ic (fortran variable in module physi-	s_rloc_container (fortran variable in module fields), 198
cal_parameters), 190	s_top (fortran variable in module init_fields), 223
rho_ratio_ma (fortran variable in module physical_parameters), 190	s_transfer_type (fortran variable in module communications), 213
rhs1 (fortran variable in module updateb_mod), 264	s_transfer_type_cont (fortran variable in module commu-
rhs1 (fortran variable in module updates_mod), 259	nications), 213
rhs1 (fortran variable in module updatewp_mod), 253	s_transfer_type_nr_end (fortran variable in module com-
rhs1 (fortran variable in module updatewps_mod), 247	munications), 214
rhs1 (fortran variable in module updatewpt_mod), 250	s_transfer_type_nr_end_cont (fortran variable in module
rhs1 (fortran variable in module updatexi_mod), 262	communications), 213
rhs1 (fortran variable in module updatez_mod), 256	sc (fortran variable in module physical_parameters), 193
rhs2 (fortran variable in module updateb_mod), 264	scale_b (fortran variable in module init_fields), 223
rint_r() (fortran function in module integration), 314	scale_s (fortran variable in module init_fields), 222
rintic() (fortran function in module integration), 313	scale_v (fortran variable in module init_fields), 223
riteration_mod (module), 269	scale_xi (fortran variable in module init_fields), 223
riterthetablocking_mod (module), 271	scanDir() (in module magic.libmagic), 177
riterthetablocking_openmp_mod (module), 273	scatter_from_rank0_to_lo() (fortran subroutine in module
rmmean (fortran variable in module output_mod), 322	communications), 215
rmmeanr (fortran variable in module outpar_mod), 339	sdens (fortran variable in module output_data), 202
rms (module), 373	sderavg() (in module magic.libmagic), 177
rms_helpers (module), 378	selectField() (in module magic.libmagic), 177
rolmean (fortran variable in module output_mod), 322	sendvals_to_rank0() (fortran subroutine in module out-
rolmeanr (fortran variable in module outpar_mod), 339	rot), 337
rolmeanru2 (fortran variable in module outpar_mod), 339	set_steering_variables() (fortran subroutine in module rit-
rot_file (fortran variable in module outrot), 335	eration_mod), 270
round_off() (fortran function in module useful), 426	set_thetablocking() (fortran subroutine in module riter-
rrmp (fortran variable in module special), 209	thetablocking_mod), 272
rstrat (fortran variable in module physical_parameters),	set_zero() (fortran subroutine in module
190	dtb_arrays_mod), 387
rstrm (fortran variable in module outto_mod), 398	set_zero() (fortran subroutine in module nonlin-
rstrm_sloc (fortran variable in module outto_mod), 398	ear_lm_mod), 279
runid (fortran variable in module output_data), 202	<pre>set_zero() (fortran subroutine in module to_arrays_mod),</pre>
runtime (fortran variable in module num_param), 188	396
runtimelimit (fortran variable in module num_param),	sigfile (fortran variable in module step_time_mod), 237
188	sigma (fortran variable in module radial_functions), 231
runtimestart (fortran variable in module num_param), 188	sigma_ratio (fortran variable in module physi-
rz (fortran variable in module geos_mod), 404	cal_parameters), 189
rz (fortran variable in module outto_mod), 398	sin36 (fortran variable in module constants), 207
rzpv (fortran variable in module geos_mod), 403	sin60 (fortran variable in module constants), 206
0	sin72 (fortran variable in module constants), 207
S	sintheta (fortran variable in module horizontal_data), 234
s0mat (fortran variable in module updates_mod), 259	sizelmb (fortran variable in module blocking), 315
s0mat_fac (fortran variable in module updates_mod), 259	sizelmb2 (fortran variable in module blocking), 316
s0pivot (fortran variable in module updates_mod), 259	sizeof_character (fortran variable in module preci-
s_ave (fortran variable in module fields_average_mod),	sion_mod), 183
372	sizeof_def_complex (fortran variable in module preci-
s_ave_global (fortran variable in module	sion_mod), 183
fields_average_mod), 371	sizeof_def_real (fortran variable in module preci-
s_bot (fortran variable in module init_fields), 222	sion_mod), 183
s_lmloc (fortran variable in module fields), 199	sizeof_integer (fortran variable in module preci-
s_lmloc_container (fortran variable in module fields), 199	sion_mod), 183

sizeof_logical (fortran variable in module preci-	step_time_mod (module), 235
sion_mod), 183	store() (fortran subroutine in module storecheckpoints),
sizeof_out_real (fortran variable in module preci-	421
sion_mod), 183	store_fields_3d() (fortran subroutine in module
sizethetab (fortran variable in module blocking), 315	out_movie), 364
sizethetabi (fortran variable in module blocking), 315	store_fields_p() (fortran subroutine in module
slice() (magic.cyl.Cyl method), 166	out_movie), 363
slice() (magic.Surf method), 145	store_fields_r() (fortran subroutine in module out_movie),
slopestrat (fortran variable in module physi-	362
cal_parameters), 191	
<u>.</u>	
smat (fortran variable in module updates_mod), 259	out_movie), 362
smat_fac (fortran variable in module updates_mod), 259	store_fields_t() (fortran subroutine in module out_movie),
smeanr (fortran variable in module outmisc_mod), 332	363
smeanr (fortran variable in module outpar_mod), 339	store_movie_frame() (fortran subroutine in module
sn2 (fortran variable in module horizontal_data), 233	out_movie), 360
sn_sub_map (fortran variable in module blocking), 315	store_movie_frame_ic() (fortran subroutine in module
solve_mat (fortran variable in module algebra), 304	out_movie_ic), 367
solve_mat_complex_rhs() (fortran subroutine in module	storecheckpoints (module), 420
algebra), 304	str2dble() (fortran subroutine in module charmanip), 428
solve_mat_complex_rhs_multi() (fortran subroutine in module algebra), 305	strat (fortran variable in module physical_parameters), 189
solve_mat_real_rhs() (fortran subroutine in module alge-	strm (fortran variable in module outto_mod), 399
bra), 305	strm_sloc (fortran variable in module outto_mod), 399
<pre>spat_spec() (magic.spectralTransforms.SpectralTransforms</pre>	subtime() (fortran subroutine in module timing), 241
method), 169	Surf (class in magic), 143
<pre>spec_spat() (magic.spectralTransforms.SpectralTransforms</pre>	
method), 170	surf() (magic.MagicPotential method), 155
spec_spat_dphi() (magic.spectralTransforms.SpectralTransf	
method), 170	surf_cmb (fortran variable in module constants), 206
spec_spat_dtheta() (magic.spectralTransforms.SpectralTran	
method), 170	symmetrize() (in module magic.libmagic), 178
spec_spat_equat() (magic.spectralTransforms.SpectralTrans	
method), 170	T
special (module), 207	4 hand (Contains a shift in moral to a start day) 205
spectra (module), 343	t_bpot (fortran variable in module output_data), 205
Spectral Transforms (class in magic.spectral Transforms),	t_bpot_start (fortran variable in module output_data), 203
169	t_bpot_stop (fortran variable in module output_data), 205
	t_cmb (fortran variable in module output_data), 203
spectrum() (fortran subroutine in module spectra), 346	t_cmb_start (fortran variable in module output_data), 204
spectrum_temp() (fortran subroutine in module spectra),	t_cmb_stop (fortran variable in module output_data), 204
347	t_graph (fortran variable in module output_data), 203
sph2cart_scal() (in module magic.graph2vtk), 160	$t_graph_start~(fortran~variable~in~module~output_data),$
sph2cart_vec() (in module magic.graph2vtk), 161	203
sph2cyl() (in module magic.cyl), 167	t_graph_stop (fortran variable in module output_data),
sph2cyl_plane() (in module magic.cyl), 167	205
spivot (fortran variable in module updates_mod), 259	t_icb_l_ave (fortran variable in module spectra), 346
sq4pi (fortran variable in module constants), 207	t_icb_1_sd (fortran variable in module spectra), 345
sric_file (fortran variable in module outrot), 335	t_icb_m_ave (fortran variable in module spectra), 346
srma_file (fortran variable in module outrot), 335	t_icb_m_sd (fortran variable in module spectra), 346
st_map (fortran variable in module blocking), 315	t_l_ave (fortran variable in module spectra), 345
st_sub_map (fortran variable in module blocking), 316	t_l_sd (fortran variable in module spectra), 345
start_fields (module), 219	t_log (fortran variable in module output_data), 205
start_file (fortran variable in module init_fields), 224	t_log_start (fortran variable in module output_data), 204
step_time() (fortran subroutine in module	t_log_stop (fortran variable in module output_data), 203
step time mod), 238	t m ave (fortran variable in module spectra) 346

t_m_sd (fortran variable in module spectra), 344 t_movie (fortran variable in module output_data), 205 t_movie_start (fortran variable in module output_data), 202 t_movie_stop (fortran variable in module output_data), 205 t_movies (fortran variable in module movie_data), 352	tdiflm (fortran variable in module dtb_mod), 383 tdiflm_lmloc (fortran variable in module dtb_mod), 383 tdiflmic (fortran variable in module dtb_mod), 383 tdiflmic_lmloc (fortran variable in module dtb_mod), 383 temp0 (fortran variable in module radial_functions), 230 temp_gather_lo (fortran variable in module communications), 214
t_pot (fortran variable in module output_data), 205	temp_r2lo (fortran variable in module communications),
t_pot_start (fortran variable in module output_data), 205 t_pot_stop (fortran variable in module output_data), 206 t_probe (fortran variable in module output_data), 203 t_probe_start (fortran variable in module output_data),	tend (fortran variable in module num_param), 187 thermo_variable (fortran variable in module num_param), 187
203 t_probe_stop (fortran variable in module output_data), 205	theta (fortran variable in module horizontal_data), 234 theta_ord (fortran variable in module horizontal_data), 234
t_r_field (fortran variable in module output_data), 205 t_r_field_start (fortran variable in module output_data), 204	theta_probe (fortran variable in module probe_mod), 414 thetaderavg() (in module magic.libmagic), 178 ThetaHeat (class in magic), 164
t_r_field_stop (fortran variable in module output_data), 204	thetas (fortran variable in module physical_parameters), 190
t_r_file (fortran variable in module output_mod), 322 t_rst (fortran variable in module output_data), 203	thetaxi (fortran variable in module physical_parameters), 192
t_rst_start (fortran variable in module output_data), 203 t_rst_stop (fortran variable in module output_data), 203	thexpnb (fortran variable in module physical_parameters), 193
t_spec (fortran variable in module output_data), 205 t_spec_start (fortran variable in module output_data), 205	thickstrat (fortran variable in module physical_parameters), 192
t_spec_stop (fortran variable in module output_data), 204	third (fortran variable in module constants), 207
t_to (fortran variable in module output_data), 204	three (fortran variable in module constants), 206
t_to_start (fortran variable in module output_data), 203	time2ms() (fortran function in module timing), 241
t_to_stop (fortran variable in module output_data), 203	timeave (fortran variable in module outto_mod), 398
t_tomovie (fortran variable in module output_data), 206	timelast (fortran variable in module outto_mod), 398
t_tomovie_start (fortran variable in module output_data), 204	timeLongitude() (magic.coeff.MagicCoeffCmb method), 150
t_tomovie_stop (fortran variable in module output_data), 204	timeLongitude() (magic.Movie method), 148 timenormlog (fortran variable in module output_mod),
t_toz (fortran variable in module output_data), 204	323
t_toz_start (fortran variable in module output_data), 202 t_toz_stop (fortran variable in module output_data), 204	timenormrms (fortran variable in module output $_{ m mod}$), 322
t_tpot (fortran variable in module output_data), 204	timeold (fortran variable in module geos_mod), 403
t_tpot_start (fortran variable in module output_data), 204 t_tpot_stop (fortran variable in module output_data), 205	timepassedlog (fortran variable in module output_mod), 322
t_vpot (fortran variable in module output_data), 204 t_vpot_start (fortran variable in module output_data), 203	timepassedrms (fortran variable in module output_mod), 323
t_vpot_stop (fortran variable in module output_data), 206	timestart (fortran variable in module num_param), 187
tadvlm (fortran variable in module dtb_mod), 383	timing (module), 240
tadvlm_lmloc (fortran variable in module dtb_mod), 383	tipdipole (fortran variable in module init_fields), 223
tadvlm_rloc (fortran variable in module dtb_mod), 383 tadvlmic (fortran variable in module dtb_mod), 383	tmagcon (fortran variable in module physical_parameters), 191
tadvlmic_lmloc (fortran variable in module dtb_mod), 383	tmeanr (fortran variable in module outmisc_mod), 332 to_arrays_mod (module), 396
tadvrlm_lmloc (fortran variable in module dtb_mod), 383	to_helpers (module), 394
tadvrlm_rloc (fortran variable in module dtb_mod), 383	tofilenhs (fortran variable in module outto_mod), 399
tag (fortran variable in module output_data), 205	tofileshs (fortran variable in module outto_mod), 399
tayfile (fortran variable in module outto_mod), 398	tomega_ic1 (fortran variable in module init_fields), 223

tomega_ic2 (fortran variable in module init_fields), 223 tomega_ma1 (fortran variable in module init_fields), 222	unknown_type (fortran type in module co- sine_transform_odd), 284
tomega_ma2 (fortran variable in module init_fields), 222	unknown_type (fortran type in module dtb_arrays_mod),
tomelm (fortran variable in module dtb_mod), 384	386
tomelm_lmloc (fortran variable in module dtb_mod), 383	unknown_type (fortran type in module leg_helper_mod),
tomelm_rloc (fortran variable in module dtb_mod), 384	289
tomerlm_lmloc (fortran variable in module dtb_mod), 383	unknown_type (fortran type in module lmmapping), 318
tomerlm_rloc (fortran variable in module dtb_mod), 384	unknown_type (fortran type in module nonlin-
TOMovie (class in magic), 155	ear_lm_mod), 278
topcond (fortran variable in module start_fields), 220 tops (fortran variable in module init_fields), 223	unknown_type (fortran type in module riteration_mod), 269
topxi (fortran variable in module init_fields), 223	unknown_type (fortran type in module riterthetablock-
topxicond (fortran variable in module start_fields), 220	ing_mod), 272
torsional_oscillations (module), 390	unknown_type (fortran type in module riterthetablock-
transform_to_grid_space() (fortran subroutine in module	ing_openmp_mod), 274
riterthetablocking_mod), 272	unknown_type (fortran type in module to_arrays_mod),
transform_to_lm_space() (fortran subroutine in module	396
riterthetablocking_mod), 272	updateb() (fortran subroutine in module updateb_mod),
transportproperties() (fortran subroutine in module ra-	265
dial_functions), 232	updateb_mod (module), 263
truncate() (magic.coeff.MagicCoeffCmb method), 151	updates() (fortran subroutine in module updates_mod), 259
truncate() (magic.coeff.MagicCoeffR method), 152 truncation (module), 184	
tscale (fortran variable in module num_param), 188	updates_ala() (fortran subroutine in module updates_mod), 260
tshift_ic1 (fortran variable in module init_fields), 223	updates_mod (module), 258
tshift_ic2 (fortran variable in module init_fields), 223	updatewp() (fortran subroutine in module up-
tshift_ma1 (fortran variable in module init_fields), 222	datewp_mod), 253
tshift_ma2 (fortran variable in module init_fields), 222	updatewp_mod (module), 251
tstrlm (fortran variable in module dtb_mod), 383	updatewps() (fortran subroutine in module up-
tstrlm_lmloc (fortran variable in module dtb_mod), 383	datewps_mod), 247
tstrlm_rloc (fortran variable in module dtb_mod), 383	updatewps_mod (module), 245
tstrrlm_lmloc (fortran variable in module dtb_mod), 383	updatewpt() (fortran subroutine in module up-
tstrrlm_rloc (fortran variable in module dtb_mod), 384	datewpt_mod), 250
two (fortran variable in module constants), 207	updatewpt_mod (module), 248
1.1	updatexi() (fortran subroutine in module updatexi_mod),
U	262
u2_p_l_ave (fortran variable in module spectra), 346	updatexi_mod (module), 261
u2_p_l_sd (fortran variable in module spectra), 345	updatez() (fortran subroutine in module updatez_mod),
u2_p_m_ave (fortran variable in module spectra), 345	256
u2_p_m_sd (fortran variable in module spectra), 345	updatez_mod (module), 255
u2_t_l_ave (fortran variable in module spectra), 345	useful (module), 422
u2_t_l_sd (fortran variable in module spectra), 345	V
u2_t_m_ave (fortran variable in module spectra), 345	•
u2_t_m_sd (fortran variable in module spectra), 346	v2as_rloc (fortran variable in module tor-
u_square_file (fortran variable in module kinetic_energy),	sional_oscillations), 391
326	v2lmr (fortran variable in module outto_mod), 398
uhmeanr (fortran variable in module outpar_mod), 339	v2lmr_rloc (fortran variable in module outto_mod), 398
ulm (fortran variable in module lmloop_data), 211	v_r_file (fortran variable in module output_mod), 322
ulmmag (fortran variable in module lmloop_data), 211	v_rigid_boundary() (fortran subroutine in module nonlin-
unknown_type (fortran type in module communications), 213	ear_bcs), 281 visc (fortran variable in module radial_functions), 231
unknown_type (fortran type in module co-	vischeatfac (fortran variable in module physi-
sine_transform_even), 286	cal_parameters), 192
5 <u></u>	vischeatr mean (fortran variable in module nower) 342

vischeatr_sd (fortran variable in module power), 342 vol_ic (fortran variable in module constants), 207 vol_oc (fortran variable in module constants), 207 vorold (fortran variable in module geos_mod), 403 vpm (fortran variable in module outto_mod), 399 vpm_sloc (fortran variable in module outto_mod), 399	write_bcmb() (fortran subroutine in module out_coeff), 368 write_coeff_r() (fortran subroutine in module out_coeff), 369 write_dtb_frame() (fortran subroutine in module out_dtb_frame), 388
vscale (fortran variable in module num_param), 188	write_movie_frame() (fortran subroutine in module out_movie), 361 write_pot() (fortran subroutine in module out_coeff), 369
w_ave (fortran variable in module fields_average_mod), 371 w_ave_global (fortran variable in module fields_average_mod), 371 w_lmloc (fortran variable in module fields), 199 w_rloc (fortran variable in module fields), 200 walltime() (fortran subroutine in module timing), 241 wdplm (fortran variable in module horizontal_data), 234 widths (fortran variable in module physical_parameters), 193 widthxi (fortran variable in module physical_parameters), 192	write_rot() (fortran subroutine in module outrot), 335 writeinfo() (fortran subroutine in module precalculations), 228 writenamelists() (fortran subroutine in module namelists), 219 writetime() (fortran subroutine in module timing), 242 writeVpEq() (in module magic.libmagic), 178 writeVTI() (magic.graph2vtk.Graph2Vtk method), 160 writeVTS() (magic.graph2vtk.Graph2Vtk method), 160 ws_global (fortran variable in module geos_mod), 403
work (fortran variable in module out_coeff), 368 work (fortran variable in module radial_der), 306 work (fortran variable in module updatewp_mod), 253 work_ld_real (fortran variable in module radial_der), 306 work_lmloc (fortran variable in module fields), 199 workb (fortran variable in module updateb_mod), 264 workb (fortran variable in module updatewp_mod), 253 workb (fortran variable in module updatewps_mod), 246 workb (fortran variable in module updatewpt_mod), 250 workb (fortran variable in module updatez_mod), 256 workc (fortran variable in module updatewps_mod), 246 workc (fortran variable in module updatewpt_mod), 249 workd (fortran variable in module updatewpt_mod), 246 workd (fortran variable in module updatewpt_mod), 249 wpass2jw() (fortran subroutine in module fft), 302 wpass3jw() (fortran subroutine in module fft), 303 wpass4jw() (fortran subroutine in module fft), 303 wpass5jw() (fortran variable in module horizontal_data), 234 wpmat (fortran variable in module updatewp_mod), 253 wpmat_fac (fortran variable in module updatewp_mod), 253	xi0mat (fortran variable in module updatexi_mod), 262 xi0mat_fac (fortran variable in module updatexi_mod), 262 xi0pivot (fortran variable in module updatexi_mod), 262 xi_ave (fortran variable in module fields_average_mod), 372 xi_ave_global (fortran variable in module fields_average_mod), 372 xi_bot (fortran variable in module init_fields), 223 xi_cond() (fortran subroutine in module init_fields), 226 xi_lmloc (fortran variable in module fields), 200 xi_lmloc_container (fortran variable in module fields), 198 xi_rloc (fortran variable in module fields), 199 xi_rloc_container (fortran variable in module fields), 199 xi_top (fortran variable in module init_fields), 223 ximat (fortran variable in module updatexi_mod), 262 ximat_fac (fortran variable in module updatexi_mod), 262 ximeanr (fortran variable in module updatexi_mod), 332 xipivot (fortran variable in module updatexi_mod), 262 Y
wppivot (fortran variable in module updatewp_mod), 253 wpsmat (fortran variable in module updatewps_mod), 246 wpsmat_fac (fortran variable in module updatewps_mod),	y10_norm (fortran variable in module constants), 207 y11_norm (fortran variable in module constants), 207 Z z10mat (fortran variable in module updatez_mod), 256 z10mat_fac (fortran variable in module updatez_mod), 256 z10pivot (fortran variable in module updatez_mod), 256 z_ave (fortran variable in module fields_average_mod), 371

z_ave_global (fortran variable in module fields_average_mod), 372 z_lmloc (fortran variable in module fields), 199 z_rloc (fortran variable in module fields), 199 zavg() (in module magic.cyl), 167 zdens (fortran variable in module output_data), 203 zderavg() (in module magic.libmagic), 178 zero (fortran variable in module constants), 206 zero tolerance (fortran variable in module algebra), 304 zerorms() (fortran subroutine in module rms), 377 zmat (fortran variable in module updatez_mod), 256 zmat_fac (fortran variable in module updatez_mod), 256 zpivot (fortran variable in module updatez_mod), 256 zs_global (fortran variable in module geos_mod), 403 zz (fortran variable in module geos_mod), 403 zz (fortran variable in module outto_mod), 398 zz_sloc (fortran variable in module outto_mod), 398