NAME

v8 — Google's JavaScript engine

SYNOPSIS

shell [*options*] [**--shell**] [*file ...*]
d8 [*options*] [**-e** *string*] [**--shell**] [[**--module**] *file...*]

OPTIONS

-- Capture all remaining arguments in JavaScript.

-e *string*
Execute *string* in V8.

--shell
Run an interactive JavaScript shell.

--help
Print flags and usage message to stdout, then exit.

--module
Execute *file* as a JavaScript module.

Note: the **--module** option is implicitly enabled for `*.mjs` files.

V8 FLAGS

Option names beginning with "**no-**" pertain to a boolean V8 flag enabled by default.

--abort-on-uncaught-exception
Abort program (dump core) when an uncaught exception is thrown.

--no-allocation-site-pretenuring
Don't pretenure with allocation sites.

--allow-natives-syntax
Allow natives syntax.

--allow-unsafe-function-constructor
Allow invoking the function constructor without security checks.

--always-compact
Perform compaction on every full GC.

--always-opt
Always try to optimize functions.

--always-osr
Always try to OSR functions.

--no-analyze-environment-liveness
Don't analyze liveness of environment slots and zap dead values.

--arm-arch
Type: String
Default: `"armv8"`

Generate instructions for the selected ARM architecture if available: armv6, armv7, armv7+sudiv or armv8.

--asm-wasm-lazy-compilation
Enable lazy compilation for asm-wasm modules.

--assert-types
Generate runtime type assertions to test the typer.

--assume-asmjs-origin
Force WASM decoder to assume input is internal asm-wasm format.

--no-async-stack-traces
Exclude async stack traces in `Error.stack`. ⟨https://mdn.io/Error.stack⟩

--block-concurrent-recompilation
Block queued jobs until released.

--budget-for-feedback-vector-allocation
Type: Int
Default: `1024`

The budget in amount of bytecode executed by a function before we decide to allocate feedback vectors.

--builtins-in-stack-traces
Show built-in functions in stack traces.

--no-cache-prototype-transitions
Don’t cache prototype transitions.

--check-icache
Check icache flushes in ARM and MIPS simulator.

--clear-exceptions-on-js-entry
Clear pending exceptions when entering JavaScript.

--clear-free-memory
Initialize free memory with 0.

--code-comments
Emit comments in code disassembly; for more readable source positions you should add `--no-concurrent-recompilation`.

--no-compact-code-space
Don’t compact code space on full collections.

--no-compilation-cache
Disable compilation cache.

--compiler-dispatcher
Enable compiler dispatcher.

--no-concurrent-array-buffer-freeing
Don’t free array buffer allocations on a background thread.

--concurrent-inlining
Run optimizing compiler’s inlining phase on a separate thread.

--no-concurrent-marking
Don’t use concurrent marking.

--no-concurrent-recompilation
Force synchronous optimisation of hot functions.

--concurrent-recompilation-delay
Type: Int
Default: `0`

Artificial compilation delay in ms.

--concurrent-recompilation-queue-length
Type: Int
Default: `8`

The length of the concurrent compilation queue.

--no-concurrent-store-buffer
Don’t use concurrent store buffer processing.

--no-concurrent-sweeping
Don’t use concurrent sweeping.

--correctness-fuzzer-suppressions
Suppress certain unspecified behaviours to ease correctness fuzzing: abort program when the stack overflows or a string exceeds maximum length (as opposed to throwing `RangeError),` ⟨https://mdn.io/RangeError),⟩ and use a fixed suppression string for error messages.

--cpu-profiler-sampling-interval
Type: Int
Default: `1000`

CPU profiler sampling interval in microseconds.

--csa-trap-on-node
Type: String
Default: `NULL`

Trigger break point when a node with given id is created in given stub. The format is:`Stub-Name,NodeId`.

--debug-code
Generate extra code (assertions) for debugging.

--debug-sim
Enable debugging the simulator.

--deopt-every-n-times
Type: Int
Default: `0`

Deoptimize every n times a deopt point is passed.

--detailed-error-stack-trace
Include arguments for each function call in the error stack frames array.

--detailed-line-info
Always generate detailed line information for CPU profiling.

--no-detect-ineffective-gcs-near-heap-limit
Don't trigger out-of-memory failure to avoid GC storm near heap limit.

--disable-abortjs
Disable AbortJS runtime function.

--disable-old-api-accessors
Disable old-style API accessors whose setters trigger through the prototype chain.

--disallow-code-generation-from-strings
Disallow `eval` and friends.

--dump-counters
Dump counters on exit.

--dump-counters-nvp
Dump counters as name-value pairs on exit.

--dump-wasm-module-path
Type: String
Default: `NULL`

Directory to dump WASM modules to.

--embedded-src
Type: String
Default: `NULL`

Path for the generated embedded data file. (`mksnapshot` only).

--embedded-variant
Type: String
Default: `NULL`

Label to disambiguate symbols in embedded data file. (`mksnapshot` only).

--enable-32dregs
Type: maybe_bool
Default: `unset`

Deprecated (use `--arm-arch` instead).

--enable-armv7
Type: maybe_bool
Default: `unset`

Deprecated (use `--arm-arch` instead).

--enable-armv8
Type: maybe_bool
Default: `unset`

Deprecated (use `--arm-arch` instead).

--no-enable-avx
Disable use of AVX instructions if available.

--no-enable-bmi1
Disable use of BMI1 instructions if available.

--no-enable-bmi2
Disable use of BMI2 instructions if available.

--no-enable-fma3
Disable use of FMA3 instructions if available.

--no-enable-lazy-source-positions
Don’t skip generating source positions during initial compile, but regenerate when actually required.

--no-enable-lzcnt
Disable use of LZCNT instruction if available.

--enable-neon
Type: maybe_bool
Default: `unset`

Deprecated (use `--arm-arch` instead).

--no-enable-one-shot-optimization
Disable size optimizations for the code that will only be executed once.

--no-enable-popcnt
Disable use of POPCNT instruction if available.

--no-enable-regexp-unaligned-accesses
Disable unaligned accesses for the regexp engine.

--no-enable-sahf
Disable use of SAHF instruction if available (X64 only).

--enable-source-at-csa-bind
Include source information in the binary at CSA bind locations.

--no-enable-sse3
Disable use of SSE3 instructions if available.

--no-enable-sse4-1
Disable use of SSE4.1 instructions if available.

--no-enable-sse4-2
Disable use of SSE4.2 instructions if available.

--no-enable-ssse3
Disable use of SSSE3 instructions if available.

--enable-sudiv
Type: maybe_bool
Default: `unset`

Deprecated (use `--arm-arch` instead).

--enable-vfp3
Type: maybe_bool
Default: `unset`

Deprecated (use `--arm-arch` instead).

--ephemeron-fixpoint-iterations
Type: Int
Default: `10`

Number of fixpoint iterations it takes to switch to linear ephemeron algorithm.

--es-staging
Internal use only.

Enable test-worthy Harmony features.

--no-experimental-inline-promise-constructor
Don't inline the `Promise` ⟨https://mdn.io/Promise⟩ constructor in TurboFan.

--experimental-new-space-growth-heuristic
Grow the new space based on the percentage of survivors instead of their absolute value.

--experimental-stack-trace-frames
Enable experimental frames (API/Builtins) and stack trace layout.

--experimental-wasm-anyref
Enable prototype anyref opcodes for WASM.

--experimental-wasm-bigint
Enable prototype JS `BigInt` ⟨https://mdn.io/BigInt⟩ support for WASM.

--no-experimental-wasm-bulk-memory
Disable prototype bulk memory opcodes for WASM.

--experimental-wasm-compilation-hints
Enable prototype compilation hints section for WASM.

--experimental-wasm-eh
Enable prototype exception handling opcodes for WASM.

--experimental-wasm-mv
Enable prototype multi-value support for WASM.

--experimental-wasm-return-call
Enable prototype return call opcodes for WASM.

--no-experimental-wasm-sat-f2i-conversions
Disable prototype saturating float conversion opcodes for WASM.

--no-experimental-wasm-se
Disable prototype sign extension opcodes for WASM.

--experimental-wasm-simd
Enable prototype SIMD opcodes for WASM.

--experimental-wasm-threads
Enable prototype thread opcodes for WASM.

--experimental-wasm-type-reflection
Enable prototype WASM type reflection in JS for WASM.

--expose-async-hooks
Expose `async_hooks` object.

--expose-cputracemark-as
Type: String
Default: `NULL`

Expose `cputracemark` extension under the specified name.

--expose-externalize-string
Expose externalize string extension.

--expose-free-buffer
Expose `freeBuffer` extension.

--expose-gc
Expose `gc` extension.

--expose-gc-as
Type: String
Default: `NULL`

Expose `gc` extension under the specified name.

--expose-inspector-scripts
Expose `injected-script-source.js` for debugging.

--expose-trigger-failure
Expose trigger-failure extension.

--no-expose-wasm
Don’t expose WASM interface to JavaScript.

--no-fast-math
Don’t enable faster, potentially less accurate, math functions.

--fast-promotion-new-space
Fast promote new space on high survival rates.

--feedback-normalization
Feed back normalization to constructors.

--no-flush-bytecode
Don’t flush bytecode that hasn’t executed recently.

--force-long-branches
Force all emitted branches to be in long mode (MIPS/PPC only).

--force-marking-deque-overflows
Force overflows of marking deque by reducing its size to 64 words.

--force-slow-path
Always take the slow path for builtins.

--frame-count
Type: Int
Default: `1`

Number of stack frames inspected by the profiler.

--function-context-specialization
Enable function context specialization in TurboFan.

--future
Implies all staged features that we want to ship in the not-too-far future.

--fuzzer-gc-analysis
Print number of allocations and enable analysis mode for GC fuzz-testing, e.g. `--stress-marking`, `--stress-scavenge`.

--fuzzer-random-seed
Type: Int
Default: `0`

Default seed for initializing fuzzer random generator (0, the default, means to use v8's random number generator seed).

--gc-experiment-background-schedule
Use new background GC schedule heuristics.

--gc-experiment-less-compaction
Use less compaction in non-memory reducing mode.

--gc-fake-mmap
Type: String
Default: `"/tmp/__v8_gc__"`

Specify the name of the file for fake gc mmap used in `ll_prof`.

--gc-freelist-strategy
Type: Int
Default: `5`

Freelist strategy to use. Supported values and their meanings are:

0 `FreeListLegacy`
1 `FreeListFastAlloc`
2 `FreeListMany`
3 `FreeListManyCached`
4 `FreeListManyCachedFastPath`
5 `FreeListManyCachedOrigin`

--gc-global
Always perform global GCs.

--gc-interval
Type: Int
Default: `-1`

Garbage collect after *N* allocations.

--gc-stats
Type: Int
Default: `0`

Used by tracing internally to enable gc statistics.

--gdbjit
Enable GDBJIT interface.

--gdbjit-dump
Dump ELF objects with debug info to disk.

--gdbjit-dump-filter
Dump only objects containing this substring.

--gdbjit-full
Enable GDBJIT interface for all code objects.

--no-global-gc-scheduling
Disable GC scheduling based on global memory.

--no-hard-abort
Don’t abort by crashing.

--harmony
Enable all completed Harmony features.

--no-harmony-dynamic-import
Disable dynamic import.

--no-harmony-import-meta
Disable `import.meta` ⟨https://mdn.io/import.meta⟩ property.

--harmony-intl-add-calendar-numbering-system
Add `calendar` and `numberingSystem` to `DateTimeFormat`.
⟨https://mdn.io/DateTimeFormat⟩

--no-harmony-intl-bigint
Disable `BigInt.prototype.toLocaleString`.
⟨https://mdn.io/BigInt.prototype.toLocaleString⟩

--no-harmony-intl-date-format-range
Disable `DateTimeFormat.formatRange`. ⟨https://mdn.io/DateTimeFormat.formatRange⟩

--harmony-intl-dateformat-day-period
Add `dayPeriod` option to `DateTimeFormat`. ⟨https://mdn.io/DateTimeFormat⟩

--harmony-intl-dateformat-fractional-second-digits
Add `fractionalSecondDigits` option to `DateTimeFormat`.
⟨https://mdn.io/DateTimeFormat⟩

--harmony-intl-dateformat-quarter
In progress.

Add `quarter` option to `DateTimeFormat`. ⟨https://mdn.io/DateTimeFormat⟩

--no-harmony-intl-datetime-style
Disable `dateStyle` and `timeStyle` for `DateTimeFormat`.
⟨https://mdn.io/DateTimeFormat⟩

--no-harmony-intl-numberformat-unified
Disable unified `Intl.NumberFormat` ⟨https://mdn.io/Intl.NumberFormat⟩ features.

--harmony-intl-segmenter
Enable `Intl.Segmenter`. ⟨https://mdn.io/Intl.Segmenter⟩

--no-harmony-namespace-exports
Disable namespace exports (`export * as foo from "bar"`).

--harmony-nullish
In progress.

Enable nullish operator.

--harmony-optional-chaining
In progress.

Enable optional chaining syntax.

--harmony-private-methods
In progress.

Enable private methods in class literals.

--no-harmony-promise-all-settled
Disable `Promise.allSettled`. ⟨https://mdn.io/Promise.allSettled⟩

--harmony-regexp-sequence
In progress.

Enable RegExp Unicode sequence properties.

--no-harmony-sharedarraybuffer
Disable `SharedArrayBuffer`. ⟨https://mdn.io/SharedArrayBuffer⟩

--no-harmony-shipping
Disable all shipped Harmony features.

--harmony-weak-refs
In progress.

Enable weak references.

--hash-seed
Type: Uint64
Default: `0`

Fixed seed to use to hash property keys (0 means random). With snapshots this option cannot override the baked-in seed.

--heap-growing-percent
Type: Int
Default: `0`

Specifies heap growing factor as (1 + heap_growing_percent / 100).

--heap-profiler-trace-objects
Dump heap object allocations/movements/size_updates.

--no-heap-profiler-use-embedder-graph
Don't use the new EmbedderGraph API to get embedder nodes.

--heap-snapshot-string-limit
Type: Int
Default: `1024`

Truncate strings to this length in the heap snapshot.

--histogram-interval
Type: Int
Default: `600000`

Time interval in ms for aggregating memory histograms.

--huge-max-old-generation-size
Increase maximum size of the old space to 4 GB for x64 systems with the physical memory bigger than 16 GB.

--no-icu-timezone-data
Don't get information about timezones from ICU.

--no-idle-time-scavenge
Don't perform scavenges in idle time.

--no-ignition-elide-noneffectful-bytecodes
Don't elide bytecodes which won't have any external effect.

--no-ignition-filter-expression-positions
Don't filter expression positions before the bytecode pipeline.

--no-ignition-reo
Don't use ignition register equivalence optimizer.

--no-ignition-share-named-property-feedback
Don't share feedback slots when loading the same named property from the same object.

--ignore-asm-unimplemented-break
Don't break for `ASM_UNIMPLEMENTED_BREAK` macros.

--no-incremental-marking
Don't use incremental marking.

--no-incremental-marking-wrappers
Don't use incremental marking for marking wrappers.

--initial-heap-size
Type: size_t
Default: `0`

Initial size of the heap (in MBytes).

--initial-old-space-size
Type: size_t
Default: `0`

Initial old space size (in MBytes).

--no-inline-accessors
Don't inline JavaScript accessors.

--no-inline-new
Don't use fast inline allocation.

--interpreted-frames-native-stack
Show interpreted frames on the native stack (useful for external profilers).

--interrupt-budget
Type: Int
Default: `147456`

Interrupt budget which should be used for the profiler counter.

--jitless
Disable runtime allocation of executable memory.

--no-lazy
Don't use lazy compilation.

--no-lazy-feedback-allocation
Don't allocate feedback vectors lazily.

--liftoff
Enable Liftoff, the baseline compiler for WebAssembly.

--lite-mode
Enable trade-off of performance for memory savings.

--ll-prof
Enable low-level Linux profiler.

--log Minimal logging (no API, code, GC, suspect, or handles samples).

--log-all
Log all events to the log file.

--log-api
Log API events to the log file.

--log-code
Log code events to the log file without profiling.

--no-log-colour
Don't use coloured output when logging.

--log-function-events
Log function events (parse, compile, execute) separately.

--log-handles
Log global handle events.

--log-instruction-file
Type: String
Default: `"arm64_inst.csv"`

AArch64 instruction statistics log file.

--log-instruction-period
Type: Int
Default: `4194304`

AArch64 instruction statistics logging period.

--log-instruction-stats
Log AArch64 instruction statistics.

--log-internal-timer-events
Time internal events.

--log-source-code
Log source code.

--log-suspect
Log suspect operations.

--logfile
Type: String
Default: `"v8.log"`

Specify the name of the log file.

--no-logfile-per-isolate
Use a single log-file for each isolate.

--manual-evacuation-candidates-selection
Test mode only flag. It allows a unit test to select evacuation candidates pages (requires `--stress-compaction`).

--map-counters
Map counters to a file.

--max-heap-size
Type: size_t
Default: `0`

Maximum size of the heap (in MBytes). Both `--max-semi-space-size` and `--max-old-space-size` take precedence. All three flags cannot be specified at the same time.

--max-inlined-bytecode-size
Type: Int
Default: `500`

Maximum size of bytecode for a single inlining.

--max-inlined-bytecode-size-absolute
Type: Int
Default: `5000`

Maximum cumulative size of bytecode considered for inlining.

--max-inlined-bytecode-size-cumulative
Type: Int
Default: `1000`

Maximum cumulative size of bytecode considered for inlining.

--max-inlined-bytecode-size-small
Type: Int
Default: `30`

Maximum size of bytecode considered for small function inlining.

--max-lazy
Ignore eager compilation hints.

--max-old-space-size
Type: size_t
Default: `0`

Maximum size of the old space (in MBytes).

--max-optimized-bytecode-size
Type: Int
Default: `61440`

Maximum bytecode size to be considered for optimization; too high values may cause the compiler to hit (release) assertions.

--max-polymorphic-map-count
Type: Int
Default: `4`

Maximum number of maps to track in `POLYMORPHIC` state.

--max-semi-space-size
Type: size_t
Default: `0`

Maximum size of a semi-space (in MBytes), the new space consists of two semi-spaces.

--max-stack-trace-source-length
Type: Int
Default: `300`

Maximum length of function source code printed in a stack trace.

--mcpu
Type: String
Default: `"auto"`

Enable optimisation for a specific CPU.

--no-memory-reducer
Don't use memory reducer.

--no-memory-reducer-for-small-heaps
Don't use memory reducer for small heaps.

--min-inlining-frequency
Type: Float
Default: `0.15`

Minimum frequency for inlining.

--min-semi-space-size
Type: size_t
Default: `0`

Minimum size of a semi-space (in MBytes), the new space consists of two semi-spaces.

--minor-mc
Perform young generation mark compact GCs.

--no-minor-mc-parallel-marking
Don't use parallel marking for the young generation.

--mock-arraybuffer-allocator
Use a mock `ArrayBuffer` ⟨https://mdn.io/ArrayBuffer⟩ allocator for testing.

--mock-arraybuffer-allocator-limit
Type: size_t
Default: `0`

Memory limit for mock `ArrayBuffer` ⟨https://mdn.io/ArrayBuffer⟩ allocator used to simulate OOM for testing.

--no-modify-field-representation-inplace
Disable in-place field representation updates.

--no-move-object-start
Disable moving of object starts.

--native-code-counters
Generate extra code for manipulating stats counters.

--never-compact
Testing only.

Never perform compaction on full GC.

--no-opt
Don’t use adaptive optimizations.

--optimize-for-size
Enable optimisations which favour memory size over execution speed.

--no-page-promotion
Don’t promote pages based on utilization.

--page-promotion-threshold
Type: Int
Default: `70`

Minimum percentage of live bytes on a page to enable fast evacuation.

--no-parallel-compaction
Don’t use parallel compaction.

--parallel-compile-tasks
Enable parallel compile tasks.

--no-parallel-marking
Don’t use parallel marking in atomic pause.

--no-parallel-pointer-update
Don’t use parallel pointer update during compaction.

--no-parallel-scavenge
Disable parallel scavenging.

--parse-only
Only parse the sources.

--no-partial-constant-pool
Disable use of partial constant pools (X64 only).

--perf-basic-prof
Enable perf Linux profiler (basic support).

--perf-basic-prof-only-functions
Only report function code ranges to perf (i.e. no stubs).

--perf-prof
Enable perf Linux profiler (experimental annotate support).

--perf-prof-annotate-wasm
Load WASM source-map and provide annotate support when used with `--perf-prof` (experimental).

--perf-prof-unwinding-info
Enable unwinding info for perf Linux profiler (experimental).

--no-polymorphic-inlining
Disable polymorphic inlining.

--predictable
Enable predictable mode.

--predictable-gc-schedule
Predictable garbage collection schedule. Fixes heap growing, idle, and memory reducing behavior.

--prepare-always-opt
Prepare for turning on always opt.

--print-all-exceptions
Print exception object and stack trace on each thrown exception.

--print-bytecode
Print bytecode generated by ignition interpreter.

--print-bytecode-filter
Type: String
Default: `"*"`

Filter for selecting which functions to print bytecode.

--print-deopt-stress
Print number of possible deopt points.

--print-opt-source
Print source code of optimized and inlined functions.

--print-wasm-code
Print WebAssembly code.

--print-wasm-stub-code
Print WebAssembly stub code.

--prof
Log statistical profiling information (implies `--log-code`).

--no-prof-browser-mode
Turn off browser-compatible mode when profiling with `--prof`.

--prof-cpp
Like `--prof`, but ignore generated code.

--prof-sampling-interval
Type: Int
Default: `1000`

Interval for `--prof` samples (in microseconds).

--profile-deserialization
Print the time it takes to deserialize the snapshot.

--random-gc-interval
Type: Int
Default: `0`

Collect garbage after **`random`**`(0,` *X*) allocations. It overrides `--gc-interval`.

--random-seed
Type: Int
Default: `0`

Default seed for initializing random generator (0, the default, means to use system random).

--no-randomize-hashes
Don't randomize hashes to avoid predictable hash collisions (with snapshots this option cannot override the baked-in seed).

--redirect-code-traces
Output deopt information and disassembly into file "code-*pid*-*isolate-id*.asm."

--redirect-code-traces-to
Type: String
Default: `NULL`

Output deopt information and disassembly into the given file.

--regexp-interpret-all
Interpret all regexp code.

--regexp-mode-modifiers
Enable inline flags in regexp.

--no-regexp-optimization
Don't generate optimized regexp code.

--regexp-tier-up
Enable regexp interpreter and tier up to the compiler.

--no-rehash-snapshot
Don't rehash strings from the snapshot to override the baked-in seed.

--reserve-inline-budget-scale-factor
Type: Float
Default: `1.2`

Maximum cumulative size of bytecode considered for inlining.

--retain-maps-for-n-gc
Type: Int
Default: `2`

Keeps maps alive for *N* old space garbage collections.

--runtime-call-stats
Report runtime call counts and times.

--sampling-heap-profiler-suppress-randomness
Use constant sample intervals to eliminate test flakiness.

--no-script-streaming
Disable parsing on background.

--semi-space-growth-factor
Type: Int
Default: `2`

Factor by which to grow the new space.

--serialization-chunk-size
Type: Uint
Default: `4096`

Custom size for serialization chunks.

--serialization-statistics
Collect statistics on serialized objects.

--sim-stack-alignment
Type: Int
Default: `8`

Stack alignment in bytes in simulator (4 or 8, 8 is default).

--sim-stack-size
Type: Int
Default: `2048`

Stack size of the ARM64, MIPS64 and PPC64 simulator in kBytes (default is 2 MB).

--single-threaded
Disable the use of background tasks.

--stack-size
Type: Int
Default: `984`

Default size of stack region v8 is allowed to use (in kBytes).

--stack-trace-limit
Type: Int
Default: `10`

Number of stack frames to capture.

--stack-trace-on-illegal
Print stack trace when an illegal exception is thrown.

--startup-blob
Type: String
Default: `NULL`

Write V8 startup blob file. (`mksnapshot` only).

--startup-src
Type: String
Default: `NULL`

Write V8 startup as C++ src. (`mksnapshot` only).

--stop-sim-at
Type: Int
Default: `0`

Simulator stop after *X* number of instructions.

--stress-compaction
Stress the GC compactor to flush out bugs (implies `--force-marking-deque-overflows`).

--stress-compaction-random
Stress GC compaction by selecting random percent of pages as evacuation candidates. It overrides `--stress-compaction`.

--stress-flush-bytecode
Stress bytecode flushing.

--stress-gc-during-compilation
Simulate GC/compiler thread race related to ⟨https://crbug.com/v8/8520⟩.

--stress-incremental-marking
Force incremental marking for small heaps and run it more often.

--stress-inline
Set high thresholds for inlining to inline as much as possible.

--stress-lazy-source-positions
Collect lazy source positions immediately after lazy compilation.

--stress-marking
Type: Int
Default: `0`

Force marking at random points between 0 and *X* (inclusive) percent of the regular marking start limit.

--stress-runs
Type: Int
Default: `0`

Number of stress runs.

--stress-sampling-allocation-profiler
Type: Int
Default: `0`

Enable sampling allocation profiler with *X* as a sample interval.

--stress-scavenge
Type: Int
Default: `0`

Force scavenge at random points between 0 and *X* (inclusive) percent of the new space capacity.

--stress-validate-asm
Try to validate everything as asm.js.

--stress-wasm-code-gc
Stress-test garbage collection of WASM code.

--suppress-asm-messages
Don't emit asm.js related messages (for golden file testing).

--target-arch
Type: String
Default: `NULL`

The `mksnapshot` target architecture. (`mksnapshot` only).

--target-os
Type: String
Default: `NULL`

The `mksnapshot` target OS. (`mksnapshot` only).

--test-small-max-function-context-stub-size
Enable testing the function context size overflow path by making the maximum size smaller.

--testing-float-flag
Type: Float
Default: `2.5`

Float-flag.

--testing-int-flag
Type: Int
Default: `13`

Testing_int_flag.

--testing-maybe-bool-flag
Type: maybe_bool
Default: `unset`

Testing_maybe_bool_flag.

--testing-prng-seed
Type: Int
Default: `42`

Seed used for threading test randomness.

--testing-string-flag
Type: String
Default: `"Hello, world!"`

String-flag.

--no-thin-strings
Disable ThinString support.

--trace
Trace function calls.

--trace-all-uses
Trace all use positions.

--trace-allocation-stack-interval
Type: Int
Default: `-1`

Print stack trace after *N* free-list allocations.

--trace-allocations-origins
Show statistics about the origins of allocations. Combine with `--no-inline-new` to track allocations from generated code.

--trace-asm-parser
Verbose logging of asm.js parse failures.

--trace-asm-scanner
Log tokens encountered by asm.js scanner.

--trace-asm-time
Log asm.js timing info to the console.

--trace-block-coverage
Trace collected block coverage information.

--trace-compiler-dispatcher
Trace compiler dispatcher activity.

--trace-concurrent-marking
Trace concurrent marking.

--trace-concurrent-recompilation
Track concurrent recompilation.

--trace-deopt
Trace optimize function deoptimization.

--trace-detached-contexts
Trace native contexts that are expected to be garbage collected.

--trace-duplicate-threshold-kb
Type: Int
Default: `0`

Print duplicate objects in the heap if their size is more than given threshold.

--trace-environment-liveness
Trace liveness of local variable slots.

--trace-evacuation
Report evacuation statistics.

−−trace-evacuation-candidates
Show statistics about the pages evacuation by the compaction.

−−trace-file-names
Include file names in trace-opt/trace-deopt output.

−−trace-for-in-enumerate
Trace for-in enumerate slow-paths.

−−trace-fragmentation
Report fragmentation for old space.

−−trace-fragmentation-verbose
Report fragmentation for old space (detailed).

−−trace-gc
Print one trace line following each garbage collection.

−−trace-gc-freelists
Print details of each freelist before and after each major garbage collection.

−−trace-gc-freelists-verbose
Print details of freelists of each page before and after each major garbage collection.

−−trace-gc-ignore-scavenger
Do not print trace line after scavenger collection.

−−trace-gc-nvp
Print one detailed trace line in name=value format after each garbage collection.

−−trace-gc-object-stats
Trace object counts and memory usage.

−−trace-gc-verbose
Print more details following each garbage collection.

−−trace-generalization
Trace map generalization.

−−trace-heap-broker
Trace the heap broker (reports on missing data only).

−−trace-heap-broker-verbose
Trace the heap broker verbosely (all reports).

−−trace-ic
Trace inline cache state transitions for tools/ic-processor.

--trace-idle-notification
Print one trace line following each idle notification.

--trace-idle-notification-verbose
Print the heap state used by the idle notification.

--trace-ignition-codegen
Trace the codegen of ignition interpreter bytecode handlers.

--trace-ignition-dispatches
Traces the dispatches to bytecode handlers by the ignition interpreter.

--trace-ignition-dispatches-output-file
Type: String
Default: `NULL`

The file to which the bytecode handler dispatch table is written (by default, the table is not written to a file).

--trace-incremental-marking
Trace progress of the incremental marking.

--trace-maps
Trace map creation.

--no-trace-maps-details
Don't log map details.

--trace-migration
Trace object migration.

--trace-minor-mc-parallel-marking
Trace parallel marking for the young generation.

--trace-mutator-utilization
Print mutator utilisation, allocation speed, GC speed.

--trace-opt
Trace lazy optimization.

--trace-opt-stats
Trace lazy optimization statistics.

--trace-opt-verbose
Extra verbose compilation tracing.

--trace-osr
Trace on-stack replacement.

--trace-parallel-scavenge
Trace parallel scavenge.

--trace-pretenuring
Trace pretenuring decisions of HAllocate instructions.

--trace-pretenuring-statistics
Trace allocation site pretenuring statistics.

--trace-protector-invalidation
Trace protector cell invalidations.

--trace-prototype-users
Trace updates to prototype user tracking.

--trace-rail
Trace RAIL mode.

--trace-representation
Trace representation types.

--trace-serializer
Print code serializer trace.

--trace-side-effect-free-debug-evaluate
Print debug messages for side-effect-free debug-evaluate for testing.

--trace-sim
Trace simulator execution.

--trace-sim-messages
Trace simulator debug messages. Implied by `--trace-sim`.

--trace-store-elimination
Trace store elimination.

--trace-stress-marking
Trace stress marking progress.

--trace-stress-scavenge
Trace stress scavenge progress.

--trace-track-allocation-sites
Trace the tracking of allocation sites.

--trace-turbo
Trace generated TurboFan IR.

--trace-turbo-alloc
Trace TurboFan's register allocator.

--trace-turbo-ceq
Trace TurboFan's control equivalence.

--trace-turbo-cfg-file
Type: String
Default: `NULL`

Trace turbo cfg graph (for C1 visualizer) to a given file name.

--trace-turbo-filter
Type: String
Default: `"*"`

Filter for tracing turbofan compilation.

--trace-turbo-graph
Trace generated TurboFan graphs.

--trace-turbo-inlining
Trace TurboFan inlining.

--trace-turbo-jt
Trace TurboFan's jump threading.

--trace-turbo-load-elimination
Trace TurboFan load elimination.

--trace-turbo-loop
Trace TurboFan's loop optimizations.

--trace-turbo-path
Type: String
Default: `NULL`

Directory to dump generated TurboFan IR to.

--trace-turbo-reduction
Trace TurboFan's various reducers.

--trace-turbo-scheduled
Trace TurboFan IR with schedule.

--trace-turbo-scheduler
Trace TurboFan's scheduler.

−−trace-turbo-trimming
Trace TurboFan’s graph trimmer.

−−no-trace-turbo-types
Don’t trace TurboFan’s types.

−−trace-unmapper
Trace the unmapping.

−−trace-verify-csa
Trace code stubs verification.

−−trace-wasm-ast-end
Type: Int
Default: `0`

End function for WASM AST trace (exclusive).

−−trace-wasm-ast-start
Type: Int
Default: `0`

Start function for WASM AST trace (inclusive).

−−trace-wasm-code-gc
Trace garbage collection of WASM code.

−−trace-wasm-memory
Print all memory updates performed in WASM code.

−−trace-wasm-serialization
Trace serialization/deserialization.

−−trace-zone-stats
Trace zone memory usage.

−−no-track-computed-fields
Don’t track computed boilerplate fields.

−−no-track-detached-contexts
Don’t track native contexts that are expected to be garbage collected.

−−no-track-double-fields
Don’t track fields with double values.

−−no-track-field-types
Don’t track field types.

−−no-track-fields
Don’t track fields with only SMI values.

−−track-gc-object-stats
Track object counts and memory usage.

−−no-track-heap-object-fields
Don’t track fields with heap values.

−−track-retaining-path
Enable support for tracking retaining path.

−−no-turbo-allocation-folding
Disable TurboFan allocation folding.

−−no-turbo-cf-optimization
Don’t optimize control flow in TurboFan.

−−turbo-control-flow-aware-allocation
Consider control flow while allocating registers.

−−no-turbo-escape
Disable escape analysis.

−−turbo-filter
Type: String
Default: **“*”**

Optimization filter for TurboFan compiler.

−−no-turbo-inline-array-builtins
Don’t inline array builtins in TurboFan code.

−−no-turbo-inlining
Disable inlining in TurboFan.

−−turbo-instruction-scheduling
Enable instruction scheduling in TurboFan.

−−no-turbo-jt
Disable jump threading in TurboFan.

−−no-turbo-load-elimination
Disable load elimination in TurboFan.

−−no-turbo-loop-peeling
Disable TurboFan loop peeling.

−−no-turbo-loop-rotation
Disable TurboFan loop rotation.

−−no-turbo-loop-variable
Disable TurboFan loop variable optimisation.

−−no-turbo-move-optimization
Don’t optimize gap moves in TurboFan.

−−turbo-profiling
Enable profiling in TurboFan.

−−no-turbo-rewrite-far-jumps
Don’t rewrite far to near jumps (ia32,x64).

−−turbo-sp-frame-access
Use stack pointer-relative access to frame wherever possible.

−−no-turbo-splitting
Don’t split nodes during scheduling in TurboFan.

−−turbo-stats
Print TurboFan statistics.

−−turbo-stats-nvp
Print TurboFan statistics in machine-readable format.

−−turbo-stats-wasm
Print TurboFan statistics of WASM compilations.

−−no-turbo-store-elimination
Disable store-store elimination in TurboFan.

−−turbo-stress-instruction-scheduling
Randomly schedule instructions to stress dependency tracking.

−−turbo-verify
Verify TurboFan graphs at each phase.

−−turbo-verify-allocation
Verify register allocation in TurboFan.

−−turbo-verify-machine-graph
Type: String
Default: `NULL`

Verify TurboFan machine graph before instruction selection.

−−no-unbox-double-arrays
Don’t automatically unbox arrays of doubles.

−−untrusted-code-mitigations
Enable mitigations for executing untrusted code.

−−use-external-strings
Use external strings for source code.

−−no-use-ic
Don’t use inline caching.

−−no-use-idle-notification
Don’t use idle notification to reduce memory footprint.

−−no-use-marking-progress-bar
Don’t use a progress bar to scan large objects in increments when incremental marking is active.

−−no-use-osr
Don’t use on-stack replacement.

−−use-strict
Enforce strict mode.

−−no-use-verbose-printer
Disable verbose printing.

−−v8-os-page-size
Type: Int
Default: `0`

Override OS page size (in KBytes).

−−no-validate-asm
Don’t validate asm.js modules before compiling.

−−no-wasm-async-compilation
Disable actual asynchronous compilation for `WebAssembly.compile`.
⟨https://mdn.io/WebAssembly.compile⟩

−−no-wasm-code-gc
Disable garbage collection of WASM code.

−−wasm-disable-structured-cloning
Disable WASM structured cloning.

−−wasm-fuzzer-gen-test
Generate a test case when running a WASM fuzzer.

--wasm-grow-shared-memory
Allow growing shared WebAssembly memory objects.

--wasm-interpret-all
Execute all WASM code in the WASM interpreter.

--wasm-lazy-compilation
Enable lazy compilation for all WASM modules.

--wasm-lazy-validation
Enable lazy validation for lazily-compiled WASM functions.

--no-wasm-math-intrinsics
Don't intrinsify some Math imports into WASM.

--wasm-max-code-space
Type: Uint
Default: `1024`

Maximum committed code space for WASM (in MB).

--wasm-max-mem-pages
Type: Uint
Default: `32767`

Maximum number of 64KiB memory pages of a WASM instance.

--wasm-max-table-size
Type: Uint
Default: `10000000`

Maximum table size of a WASM instance.

--wasm-no-bounds-checks
Disable bounds checks (performance testing only).

--wasm-no-stack-checks
Disable stack checks (performance testing only).

--wasm-num-compilation-tasks
Type: Int
Default: `10`

Number of parallel compilation tasks for WASM.

--wasm-opt
Enable WASM optimization.

−−no-wasm-shared-code
Don’t share code underlying a WASM module when it is transferred.

−−no-wasm-shared-engine
Don’t share one WASM engine between all isolates within a process.

−−wasm-staging
Enable staged WASM features.

−−wasm-test-streaming
Use streaming compilation instead of async compilation for tests.

−−wasm-tier-mask-for-testing
Type: Int
Default: `0`

Bitmask of functions to compile with TurboFan instead of Liftoff.

−−no-wasm-tier-up
Disable WASM baseline compilation and tier up to the optimizing compiler.

−−no-wasm-trap-handler
Don’t use signal handlers to catch out of bounds memory access in WASM (currently Linux x86_64 only).

−−wasm-write-protect-code-memory
Write protect code memory on the WASM native heap.

−−no-win64-unwinding-info
Disable unwinding info for Windows/x64.

−−no-write-protect-code-memory
Don’t write protect code memory.

−−no-young-generation-large-objects
Don’t allocate large objects by default in the young generation large object space.

SEE ALSO

node(1)

AUTHORS