## yhOS documentation

aceinetx (c) 2022-2025

## System calls

id (%eax)	%ebx	%ecx	%edx	description
SYS_WRITEC - 0	character	-	-	Prints a character to the screen
SYS_WRITE -	buffer	-	-	Prints a null terminated string to the screen
SYS_GETS - 2	buffer	length	-	Requests a string from the user
SYS_VFSWRI TE - 3	filename[VFS_ MAX_FILE_N AME]	buffer[VFS_M AX_FILE_SIZ E]	-	Writes a file to the virtual file system. If no file is found it will create it (if there is enough space). Returns 0 in eax if fails. Returns a content address if doesn't fail
SYS_VFSREA D - 4	filename[VFS_ MAX_FILE_N AME]		-	Reads a file from the virtual file system. Returns 0 in eax if fails. Returns a content address if doesn't fail

A writec system call example in flat assembler:

```
mov eax, SYS_WRITEC mov ebx, 0x45 int 0x80
```

And in C:

syscall(SYS\_WRITEC, 'E'); //Requires
syscall.h

## Virtual file system

yhOS has a mechanism called "Virtual file system". You can think of it like a virtual hard drive, it stores every file in RAM which unloads on restart.

Virtual file system is structured as a array of a structure called vfs\_file. This structure consists of 2 variables: a filename[VFS\_MAX\_FILE\_NAME] and content[VFS\_MAX\_FILE\_SIZE]

By default, yhOS allocates space for only 512 files, file name size is 16 bytes and file content is 4096 bytes.

System calls that start with SYS\_VFS are not for I/O but for the virtual file system