hypre Reference Manual: Babel-based Interface in C

Contents

1		rix and Vector Views (Conceptual Interfaces) —	5
	1.1	IJ Matrix View —	
	1.2	IJ Vector View —	
	1.3	Struct Matrix View —	15
	1.4	Struct Vector View —	20
	1.5	SemiStructured Matrix View —	23
	1.6	SemiStructured Vector View —	28
2	Oper	rator Interface —	35
3	Vecto	or Interface —	39
4		rices and Vectors —	42
	4.1	IJParCSR Matrix —	
	4.2	IJParCSR Vector —	53
	4.3	Struct Matrix —	59
	4.4	Struct Vector —	
	4.5	SemiStructured Matrix —	
	4.6	SemiStructured Vector —	
	4.7	SemiStructured ParCSR Matrix —	92
	4.8	SemiStructured ParCSR Vector —	103
5		er Interface —	
	5.9	Identity Solver (does nothing) —	
	5.10	Hybrid Solver —	123
6		SR Matrix Solvers — Linear solvers for sparse matrix systems	
	6.1	ParCSRDiagScale Solver —	
	6.2	ParCSR BoomerAMG Solver —	
	6.3	ParCSR Euclid Solver —	
	6.4	ParCSR Schwarz Solver —	
	6.5	ParCSR ParaSails Solver —	
	6.6	ParCSR Pilut Solver —	164
7	Struc	ctured Matrix Solvers — Linear solvers for struct matrix systems	171
	7.1	StructDiagScale Solver —	171
	7.2	Struct Jacobi Solver —	178
	7.3	Struct PFMG Solver —	184
	7.4	Struct SMG Solver —	191
8		Structured Matrix Solvers — Linear solvers for semi-struct matrix systems	198
	8.1	SemiStruct DiagScale Solver —	198
	8.2	Struct Split Solver —	205

$\ensuremath{\mathit{hypre}}$ Reference Manual: Babel-based Interface in C

9	Prece	onditionedSolver Interface —	212
10	Prece 10.1	PCG Preconditioned Solver —	
	10.2	GMRES Preconditioned Solver — $\hfill \ldots$	221
	10.3	BiCGSTAB Preconditioned Solver —	227
	10.4	CGNR Preconditioned Solver —	234
11	Othe	r —	
	11.1	MPI Communicator —	241
12	Struc	t Grid, etc. —	244
	12.1	Struct Grid —	244
	12.2	Struct Stencil —	248
13	Semi-	Structured Grid, etc. —	253
	13.1	Semi-Structured Graph —	253
	13.2	${\bf Semi-Structured\ Grid\\qquad \qquad }$	258
	13.3	Semi-Structured Stencil —	262
	13.4	Semi-Structured Variable —	
	Class	Granh	267

Copyright (c) 2006 The Regents of the University of California. Produced at the Lawrence Livermore National Laboratory. Written by the HYPRE team. UCRL-CODE-222953. All rights reserved.

This file is part of HYPRE (see http://www.llnl.gov/CASC/hypre/). Please see the COPY-RIGHT_and_LICENSE file for the copyright notice, disclaimer, contact information and the GNU Lesser General Public License.

HYPRE is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License (as published by the Free Software Foundation) version 2.1 dated February 1999.

HYPRE is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the IMPLIED WARRANTY OF MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the terms and conditions of the GNU General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this program; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA

1

Matrix and Vector Views (Conceptual Interfaces)

Names		
1.1	IJ Matrix View	
1.2	IJ Vector View	
		10
1.3	Struct Matrix View	
		15
1.4	Struct Vector View	
		20
1.5	SemiStructured Matrix View	
		23
1.6	SemiStructured Vector View	
		28

1.1

IJ Matrix View

Names		
1.1.1	struct bHYPRE_IJMatrixViewobject Symbol "bHYPRE	7
1.1.2	extern C bHYPRE_IJMatrixView bHYPRE_IJMatrixViewconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	7
1.1.3	SIDL_C_INLINE_DECL int32_t bHYPRE_IJMatrixView_SetLocalRange (bHYPRE_IJMatrixView self,	8
1.1.4	int32_t bHYPRE_IJMatrixView_SetValues (bHYPRE_IJMatrixView self,	8
1.1.5	$\mathrm{int}32$ _t	

	bHYPRE_IJMatrixView_AddToValues (bHYPRE_IJMatrixView self, int32_t nrows, int32_t* ncols, int32_t* rows, int32_t* cols, double* values, int32_t nnonzeros, sidl_BaseInterface *_ex)	
	Adds to values for nrows of the matrix	9
	SIDL_C_INLINE_DECL int32_t bHYPRE_IJMatrixView_GetLocalRange (bHYPRE_IJMatrixView self, int32_t* ilower, int32_t* iupper, int32_t* ilower, int32_t* iupper,	
	int32_t* jlower, int32_t* jupper, sidl_BaseInterface *_ex)	
	Gets range of rows owned by this processor and range of column partitioning for this processor	
	$\mathrm{int}32$ _{t}	
	bHYPRE_IJMatrixView_GetRowCounts (bHYPRE_IJMatrixView self, int32_t nrows, int32_t* rows, int32_t* ncols, sidl_BaseInterface *_ex)	
	Gets number of nonzeros elements for nrows rows specified in rows and returns them in ncols, which needs to be allocated by the user	
1.1.6	int32_t bHYPRE_IJMatrixView_GetValues (bHYPRE_IJMatrixView self, int32_t nrows, int32_t* ncols,	
	int32_t* rows, int32_t* cols, double* values, int32_t nnonzeros, sidl_BaseInterface *_ex)	
	Gets values for nrows rows or partial rows of the matrix	9
1.1.7	SIDL_C_INLINE_DECL int32_t bHYPRE_IJMatrixView_SetRowSizes (bHYPRE_IJMatrixView self, int32_t* sizes, int32_t nrows,	
	sidl_BaseInterface *_ex) (Optional) Set the max number of nonzeros to expect in each row	9
1.1.8	SIDL_C_INLINE_DECL int32_t	Ü
	bHYPRE_IJMatrixView_Print (bHYPRE_IJMatrixView self, const char* filename, sidl_BaseInterface *_ex)	
	Print the matrix to file	10
1.1.9	SIDL_C_INLINE_DECL_int32_t bHYPRE_IJMatrixView_Read (bHYPRE_IJMatrixView self,	
	const char* filename, bHYPRE_MPICommunicator comm, sidl_BaseInterface *_ex)	
	Read the matrix from file	10
	_ex Cast method for interface and class type conversions	
	void*	
	bHYPRE_IJMatrixViewcast2 (void* obj, const char* type, sidl_BaseInterface *_ex)	
	String cast method for interface and class type conversions	
	SIDL_C_INLINE_DECL void	

bHYPRE_IJMatrixView_exec (bHYPRE_IJMatrixView self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex) Select and execute a method by name SIDL_C_INLINE_DECL char* bHYPRE_IJMatrixView__getURL (bHYPRE_IJMatrixView self, sidl_BaseInterface *_ex) Get the URL of the Implementation of this object (for RMI) SIDL_C_INLINE_DECL_void bHYPRE_IJMatrixView__raddRef (bHYPRE_IJMatrixView self, sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance SIDL_C_INLINE_DECL sidl_bool bHYPRE_IJMatrixView__isRemote (bHYPRE_IJMatrixView self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local

sidl_bool

bHYPRE_IJMatrixView__isLocal (bHYPRE_IJMatrixView self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

 $**_ex$

 $Cast\ method\ for\ interface\ and\ class\ type\ conversions$

1.1.10 **_ex

RMI connector function for the class

1.1.1

struct bHYPRE_IJMatrixView_object

Symbol "bHYPRE.IJMatrixView" (version 1.0.0)

This interface represents a linear-algebraic conceptual view of a linear system. The 'I' and 'J' in the name are meant to be mnemonic for the traditional matrix notation A(I,J).

1.1.2

extern C bHYPRE_IJMatrixView bHYPRE_IJMatrixView_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

1.1.3

SIDL_C_INLINE_DECL int32_t bHYPRE_IJMatrixView_SetLocalRange (bHYPRE_IJMatrixView self, int32_t ilower, int32_t ilower, int32_t jlower, int32_t jupper, sidl_BaseInterface *_ex)

Set the local range for a matrix object. Each process owns some unique consecutive range of rows, indicated by the global row indices ilower and iupper. The row data is required to be such that the value of ilower on any process p be exactly one more than the value of iupper on process p-1. Note that the first row of the global matrix may start with any integer value. In particular, one may use zero- or one-based indexing.

For square matrices, jlower and jupper typically should match ilower and iupper, respectively. For rectangular matrices, jlower and jupper should define a partitioning of the columns. This partitioning must be used for any vector v that will be used in matrix-vector products with the rectangular matrix. The matrix data structure may use jlower and jupper to store the diagonal blocks (rectangular in general) of the matrix separately from the rest of the matrix.

Collective.

1.1.4

int32_t bHYPRE_IJMatrixView_SetValues (bHYPRE_IJMatrixView self, int32_t nrows, int32_t* ncols, int32_t* rows, int32_t* cols, double* values, int32_t nnonzeros, sidl_BaseInterface *_ex)

Sets values for nrows of the matrix. The arrays ncols and rows are of dimension nrows and contain the number of columns in each row and the row indices, respectively. The array cols contains the column indices for each of the rows, and is ordered by rows. The data in the values array corresponds directly to the column entries in cols. The last argument is the size of the cols and values arrays, i.e. the total number of nonzeros being provided, i.e. the sum of all values in ncols. This functin erases any previous values at the specified locations and replaces them with new ones, or, if there was no value there before, inserts a new one.

Not collective.

1.1.5

 $int32_t$

bHYPRE_IJMatrixView_AddToValues (bHYPRE_IJMatrixView self, int32_t nrows, int32_t* ncols, int32_t* rows, int32_t* cols, double* values, int32_t nnonzeros, sidl_BaseInterface *_ex)

Adds to values for nrows of the matrix. Usage details are analogous to SetValues. Adds to any previous values at the specified locations, or, if there was no value there before, inserts a new one.

Not collective.

1.1.6

 $int32_t$

bHYPRE_IJMatrixView_GetValues (bHYPRE_IJMatrixView self, int32_t nrows, int32_t* ncols, int32_t* rows, int32_t* cols, double* values, int32_t nnonzeros, sidl_BaseInterface *_ex)

Gets values for nrows rows or partial rows of the matrix. Usage details are analogous to SetValues.

1.1.7

SIDL_C_INLINE_DECL int32_t bHYPRE_IJMatrixView_SetRowSizes (bHYPRE_IJMatrixView self, int32_t* sizes, int32_t nrows, sidl_BaseInterface *_ex)

(Optional) Set the max number of nonzeros to expect in each row. The array sizes contains estimated sizes for each row on this process. The integer nrows is the number of rows in the local matrix. This call can significantly improve the efficiency of matrix construction, and should always be utilized if possible.

Not collective.

1.1.8

SIDL_C_INLINE_DECL int32_t bHYPRE_IJMatrixView_Print (bHYPRE_IJMatrixView self, const char* filename, sidl_BaseInterface *_ex)

Print the matrix to file. This is mainly for debugging purposes.

1.1.9

SIDL_C_INLINE_DECL int32_t bHYPRE_IJMatrixView_Read (bHYPRE_IJMatrixView self, const char* filename, bHYPRE_MPICommunicator comm, sidl_BaseInterface *_ex)

Read the matrix from file. This is mainly for debugging purposes.

_ 1.1.10 ____

struct bHYPRE_IJMatrixView__object* bHYPRE_IJMatrixView__connectI const char * url sidl_bool ar struct sidl_BaseInterface__object **_ex

RMI connector function for the class. (no addref)

_ 1.2 __

Names

IJ Vector View

1.2.3 SIDL_C_INLINE_DECL int32_t

	bHYPRE_IJVectorView_SetLocalRange (bHYPRE_IJVectorView self, int32_t jlower, int32_t jupper, sidl_BaseInterface *_ex)	
	Set the local range for a vector object	13
1.2.4	int32_t bHYPRE_IJVectorView_SetValues (bHYPRE_IJVectorView self,	10
	Sets values in vector	13
1.2.5	int32_t bHYPRE_IJVectorView_AddToValues (bHYPRE_IJVectorView self,	
	Adds to values in vector	13
	SIDL_C_INLINE_DECL int32_t bHYPRE_IJVectorView_GetLocalRange (bHYPRE_IJVectorView self,	
1.2.6	$\mathrm{int}32$ _t	
	bHYPRE_IJVectorView_GetValues (bHYPRE_IJVectorView self, int32_t nvalues, int32_t* indices, double* values, sidl_BaseInterface *_ex) Gets values in vector	14
1.2.7	SIDL_C_INLINE_DECL int32_t bHYPRE_IJVectorView_Print (bHYPRE_IJVectorView self,	
	Print the vector to file	14
1.2.8	SIDL_C_INLINE_DECL int32_t bHYPRE_IJVectorView_Read (bHYPRE_IJVectorView self,	
	Read the vector from file	14
	_ex Cast method for interface and class type conversions	
	void* bHYPRE_IJVectorViewcast2 (void* obj, const char* type,	
	String cast method for interface and class type conversions	
	SIDL_C_INLINE_DECL void	

bHYPRE_IJVectorView_exec (bHYPRE_IJVectorView self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex) Select and execute a method by name SIDL_C_INLINE_DECL char* bHYPRE_IJVectorView__getURL (bHYPRE_IJVectorView self, sidl_BaseInterface *_ex) Get the URL of the Implementation of this object (for RMI) SIDL_C_INLINE_DECL_void bHYPRE_IJVectorView_raddRef (bHYPRE_IJVectorView self, sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance SIDL_C_INLINE_DECL sidl_bool bHYPRE_IJVectorView__isRemote (bHYPRE_IJVectorView self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local $sidl_bool$ bHYPRE_IJVectorView__isLocal (bHYPRE_IJVectorView self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local **_ex Cast method for interface and class type conversions $**_ex$ 1.2.9

RMI connector function for the class

1.2.1

struct bHYPRE_IJVectorView__object

Symbol "bHYPRE.IJVectorView" (version 1.0.0)

1.2.2

extern C bHYPRE_IJVectorView **bHYPRE_IJVectorView_connect** (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

1.2.3

SIDL_C_INLINE_DECL int32_t bHYPRE_IJVectorView_SetLocalRange (bHYPRE_IJVectorView self, int32_t jlower, int32_t jupper, sidl_BaseInterface *_ex)

Set the local range for a vector object. Each process owns some unique consecutive range of vector unknowns, indicated by the global indices jlower and jupper. The data is required to be such that the value of jlower on any process p be exactly one more than the value of jupper on process p-1. Note that the first index of the global vector may start with any integer value. In particular, one may use zero- or one-based indexing.

Collective.

1.2.4

bHYPRE_IJVectorView_SetValues (bHYPRE_IJVectorView self, int32_t nvalues, int32_t* indices, double* values, sidl_BaseInterface *_ex)

Sets values in vector. The arrays values and indices are of dimension nvalues and contain the vector values to be set and the corresponding global vector indices, respectively. Erases any previous values at the specified locations and replaces them with new ones.

Not collective.

1.2.5

bHYPRE_IJVectorView_AddToValues (bHYPRE_IJVectorView self, int32_t nvalues, int32_t* indices, double* values, sidl_BaseInterface *_ex)

Adds to values in vector. Usage details are analogous to SetValues.

Not collective.

1.2.6

 $int32_t$

bHYPRE_IJVectorView_GetValues (bHYPRE_IJVectorView self, int32_t nvalues, int32_t* indices, double* values, sidl_BaseInterface *_ex)

Gets values in vector. Usage details are analogous to SetValues.

Not collective.

1.2.7

SIDL_C_INLINE_DECL int32_t bHYPRE_IJVectorView_Print (bHYPRE_IJVectorView self, const char* filename, sidl_BaseInterface *_ex)

Print the vector to file. This is mainly for debugging purposes.

__ 1.2.8 __

SIDL_C_INLINE_DECL int32_t bHYPRE_IJVectorView_Read (bHYPRE_IJVectorView self, const char* filename, bHYPRE_MPICommunicator comm, sidl_BaseInterface *_ex)

Read the vector from file. This is mainly for debugging purposes.

__ 1.2.9 ____

RMI connector function for the class. (no addref)

1.3

Struct Matrix View

Names		
1.3.1	struct bHYPRE_StructMatrixViewobject Symbol "bHYPRE	
1.3.2	extern C bHYPRE_StructMatrixView bHYPRE_StructMatrixView_connect (const char *,	
	RMI connector function for the class	
1.3.3	SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrixView_SetGrid (bHYPRE_StructMatrixView self, bHYPRE_StructGrid grid, sidl_BaseInterface *_ex)	
	Set the grid on which vectors are defined	
1.3.4	SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrixView_SetStencil (bHYPRE_StructMatrixView self, bHYPRE_StructStencil stencil, sidl_BaseInterface *_ex) Set the stencil	
1.3.5	int32_t bHYPRE_StructMatrixView_SetValues (bHYPRE_StructMatrixView self, int32_t* index, int32_t dim, int32_t num_stencil_indices, int32_t* stencil_indices, double* values, sidl_BaseInterface *_ex)	
	Set matrix values at grid point, given by "index"	
1.3.6	int32_t bHYPRE_StructMatrixView_SetBoxValues (bHYPRE_StructMatrixView self, int32_t* ilower, int32_t* iloper, int32_t dim, int32_t num_stencil_indices, int32_t* stencil_indices, double* values, int32_t nvalues, sidl_BaseInterface *_ex) Set matrix values throughout a box in the grid, specified by its lower and	
	upper corners	
1.3.7	SIDL_C_INLINE_DECL_int32_t bHYPRE_StructMatrixView_SetNumGhost (bHYPRE_StructMatrixView self, int32_t* num_ghost, int32_t dim2, sidl_BaseInterface *_ex)	
	Set the number of ghost zones, separately on the lower and upper sides for each dimension	
	SIDL_C_INLINE_DECL_int32_t	

```
bHYPRE_StructMatrixView_SetSymmetric ( bHYPRE_StructMatrixView
                                                          self, int32_t symmetric,
                                                          sidl_BaseInterface *_ex)
                   Call SetSymmetric with symmetric=1 to turn on symmetric matrix storage
                   if available
1.3.8
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_StructMatrixView_SetConstantEntries (
                                                                bHYPRE_StructMatrixView
                                                                self, int32_t
                                                                num_stencil_constant_points,
                                                                int32_t*
                                                                stencil_constant_points,
                                                                sidl_BaseInterface *_ex)
                                                                                              19
                   State which stencil entries are constant over the grid ......
1.3.9
            int32_t
            bHYPRE_StructMatrixView_SetConstantValues (
                                                               bHYPRE_StructMatrixView
                                                               self, int32_t
                                                               num_stencil_indices,
                                                               int32_t* stencil_indices,
                                                               double* values.
                                                               sidl_BaseInterface *_ex)
                   Provide values for matrix coefficients which are constant throughout the grid,
                   one value for each stencil point .....
                                                                                              19
            _ex
                   Cast method for interface and class type conversions
            void*
            bHYPRE_StructMatrixView__cast2 (void* obj, const char* type,
                                                  sidl_BaseInterface *_ex)
                   String cast method for interface and class type conversions
            SIDL_C_INLINE_DECL_void
            bHYPRE_StructMatrixView_exec ( bHYPRE_StructMatrixView self,
                                                 const char* methodName,
                                                 sidl_rmi_Call inArgs,
                                                 sidl_rmi_Return outArgs,
                                                 sidl_BaseInterface *_ex)
                   Select and execute a method by name
            SIDL_C_INLINE_DECL char*
            bHYPRE_StructMatrixView_getURL ( bHYPRE_StructMatrixView self,
                                                     sidl_BaseInterface *_ex)
                   Get the URL of the Implementation of this object (for RMI)
            SIDL_C_INLINE_DECL void
            bHYPRE_StructMatrixView_raddRef ( bHYPRE_StructMatrixView self,
                                                     sidl_BaseInterface *_ex)
                   On a remote object, addrefs the remote instance
            SIDL_C_INLINE_DECL sidl_bool
            bHYPRE_StructMatrixView_isRemote ( bHYPRE_StructMatrixView self,
                                                      sidl_BaseInterface *_ex)
                   TRUE if this object is remote, false if local
            sidl_bool
```

bHYPRE_StructMatrixView__isLocal (bHYPRE_StructMatrixView self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

**_ex

Cast method for interface and class type conversions

**_ex

RMI connector function for the class

_ 1.3.1 ____

1.3.10

struct bHYPRE_StructMatrixView_object

Symbol "bHYPRE.StructMatrixView" (version 1.0.0)

1.3.2

extern C bHYPRE_StructMatrixView bHYPRE_StructMatrixView_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

1.3.3

SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrixView_SetGrid (bHYPRE_StructMatrixView self, bHYPRE_StructGrid grid, sidl_BaseInterface *_ex)

Set the grid on which vectors are defined. This and the stencil determine the matrix structure.

134

SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrixView_SetStencil (bHYPRE_StructMatrixView self, bHYPRE_StructStencil stencil, sidl_BaseInterface *_ex)

Set the stencil. This and the grid determine the matrix structure.

__ 1.3.5 _

 $int32_t$

bHYPRE_StructMatrixView_SetValues (bHYPRE_StructMatrixView self, int32_t* index, int32_t dim, int32_t num_stencil_indices, int32_t* stencil_indices, double* values, sidl_BaseInterface *_ex)

Set matrix values at grid point, given by "index". You can supply values for one or more positions in the stencil. "index" is an array of size "dim"; and "stencil_indices" and "values" are arrays of size "num_stencil_indices".

_ 1.3.6 _

 $int32_t$

bHYPRE_StructMatrixView_SetBoxValues (bHYPRE_StructMatrixView self, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t num_stencil_indices, int32_t* stencil_indices, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set matrix values throughout a box in the grid, specified by its lower and upper corners. You can supply these values for one or more positions in the stencil. Thus the total number of matrix values you supply, "nvalues", is num_stencil_indices x box_size, where box_size is the number of grid points in the box. The values array should be organized so all values for a given box point are together (i.e., the stencil index is the most rapidly varying). "ilower" and "iupper" are arrays of size "dim", "stencil_indices" is an array of size "num_stencil_indices", and "values" is an array of size "nvalues".

1.3.7

SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrixView_SetNumGhost (bHYPRE_StructMatrixView self, int32_t* num_ghost, int32_t dim2, sidl_BaseInterface *_ex)

Set the number of ghost zones, separately on the lower and upper sides for each dimension. "num_ghost" is an array of size "dim2", twice the number of dimensions

1.3.8

SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrixView_SetConstantEntries (

bHYPRE_StructMatrixView self, int32_t num_stencil_constant_points, int32_t* stencil_constant_points, sidl_BaseInterface *_ex)

State which stencil entries are constant over the grid. Supported options are: (i) none (the default), (ii) all (stencil_constant_points should include all stencil points) (iii) all entries but the diagonal.

1.3.9

int32_t bHYPRE_StructMatrixView_SetConstantValues (

bHYPRE_StructMatrixView self, int32_t num_stencil_indices, int32_t* stencil_indices, double* values, sidl_BaseInterface *_ex)

Provide values for matrix coefficients which are constant throughout the grid, one value for each stencil point. "stencil_indices" and "values" is each an array of length "num_stencil_indices"

_ 1.3.10 _

struct bHYPRE_StructMatrixView__object* bHYPRE_StructMatrixView__connectI const char * url sidl_bool ar struct sidl_BaseInterface__object ***_ex

RMI connector function for the class. (no addref)

1.4

Struct Vector View

Names		
1.4.1	struct bHYPRE_StructVectorView_object Symbol "bHYPRE	2
1.4.2	extern C bHYPRE_StructVectorView bHYPRE_StructVectorView_connect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	2
	SIDL_C_INLINE_DECL_int32_t bHYPRE_StructVectorView_SetGrid (bHYPRE_StructVectorView self, bHYPRE_StructGrid grid, sidl_BaseInterface *_ex)	
	Set the grid on which vectors are defined	
1.4.3	SIDL_C_INLINE_DECL int32_t bHYPRE_StructVectorView_SetNumGhost (bHYPRE_StructVectorView self, int32_t* num_ghost, int32_t dim2, sidl_BaseInterface *_ex) Set the number of ghost zones, separately on the lower and upper sides for	
	each dimension	2
1.4.4	SIDL_C_INLINE_DECL int32_t bHYPRE_StructVectorView_SetValue (bHYPRE_StructVectorView self,	2
1.4.5	int32_t bHYPRE_StructVectorView_SetBoxValues (bHYPRE_StructVectorView self, int32_t* ilower, int32_t* iupper, int32_t dim, double* values, int32_t nvalues, sidl_BaseInterface *_ex) Set the values of all vector coefficient for grid points in a box	2
	_ex Cast method for interface and class type conversions	
	void* bHYPRE_StructVectorViewcast2 (void* obj, const char* type, sidl_BaseInterface *_ex)	
	String cast method for interface and class type conversions	
	SIDL_C_INLINE_DECL void	

bHYPRE_StructVectorView_exec (bHYPRE_StructVectorView self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex) Select and execute a method by name SIDL_C_INLINE_DECL char* bHYPRE_StructVectorView__getURL (bHYPRE_StructVectorView self, sidl_BaseInterface *_ex) Get the URL of the Implementation of this object (for RMI) SIDL_C_INLINE_DECL_void bHYPRE_StructVectorView_raddRef (bHYPRE_StructVectorView self, sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance SIDL_C_INLINE_DECL sidl_bool bHYPRE_StructVectorView__isRemote (bHYPRE_StructVectorView self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local sidl_bool bHYPRE_StructVectorView__isLocal (bHYPRE_StructVectorView self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local $**_ex$ Cast method for interface and class type conversions

RMI connector function for the class

1.4.1

1.4.6

 $**_ex$

struct bHYPRE_StructVectorView_object

Symbol "bHYPRE.StructVectorView" (version 1.0.0)

1.4.2

extern C bHYPRE_StructVectorView **bHYPRE_StructVectorView__connect** (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

1.4.3

SIDL_C_INLINE_DECL int32_t bHYPRE_StructVectorView_SetNumGhost (bHYPRE_StructVectorView self, int32_t* num_ghost, int32_t dim2, sidl_BaseInterface *_ex)

Set the number of ghost zones, separately on the lower and upper sides for each dimension. "num_ghost" is an array of size "dim2", twice the number of dimensions.

1.4.4

SIDL_C_INLINE_DECL int32_t bHYPRE_StructVectorView_SetValue (bHYPRE_StructVectorView self, int32_t* grid_index, int32_t dim, double value, sidl_BaseInterface *_ex)

Set the value of a single vector coefficient, given by "grid_index". "grid_index" is an array of size "dim", where dim is the number of dimensions.

1.4.5

bHYPRE_StructVectorView_SetBoxValues (bHYPRE_StructVectorView self, int32_t* ilower, int32_t* iupper, int32_t dim, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set the values of all vector coefficient for grid points in a box. The box is defined by its lower and upper corners in the grid. "ilower" and "iupper" are arrays of size "dim", where dim is the number of dimensions. The "values" array has size "nvalues", which is the number of grid points in the box.

_ 1.4.6 _

struct bHYPRE_StructVectorView__object* bHYPRE_StructVectorView__connectI const char * url sidl_bool ar struct sidl_BaseInterface__object ***_ex

RMI connector function for the class. (no addref)

_ 1.5 _

SemiStructured Matrix View

Names		
1.5.1	struct bHYPRE_SStructMatrixViewobject Symbol "bHYPRE	25
1.5.2	extern C bHYPRE_SStructMatrixView	
	bHYPRE_SStructMatrixView_connect (const char *,	
	sidl_BaseInterface *_ex)	
	RMI connector function for the class	25
1.5.3	SIDL_C_INLINE_DECL_int32_t	
1.0.0	bHYPRE_SStructMatrixView_SetGraph (bHYPRE_SStructMatrixView	
	self,	
	bHYPRE_SStructGraph graph,	
	sidl_BaseInterface *_ex)	
	Set the matrix graph	26
1.5.4	${ m int}32$ _t	
1.0.4	bHYPRE_SStructMatrixView_SetValues (bHYPRE_SStructMatrixView	
	self, int32_t part,	
	int32_t* index, int32_t dim,	
	int32_t var, int32_t nentries,	
	int32_t* entries, double* values,	
	sidl_BaseInterface *_ex)	
	Set matrix coefficients index by index	26
1 7 7		
1.5.5	int32_t	
	bHYPRE_SStructMatrixView_SetBoxValues (bHYPRE_SStructMatrixView	
	self, int32_t part,	
	$ \frac{1}{1} \frac{1} \frac$	
	$ \frac{11132 - 110 \text{WeI}}{11132 - 110 \text{WeI}}, $ $ \frac{11132 - 110 \text{WeI}}{11132 - 110 \text{WeI}}, $ $ \frac{11132 - 110 \text{WeI}}{11132 - 110 \text{WeI}}, $ $ \frac{11132 - 110 \text{WeI}}{11132 - 110 \text{WeI}}, $	
	int32_t var, int32_t nentries,	
	$int32t^*$ entries,	
	double* values,	
	int32_t nvalues,	
	sidl_BaseInterface *_ex)	
	Set matrix coefficients a box at a time	26
1.5.6	${ m int}32$ _t	
1.5.0	$bHYPRE_SStructMatrixView_AddToValues$ (
	bHYPRE_SStructMatrixView_Add To Values (bHYPRE_SStructMatrixView	
	self, int32_t part,	
	int32_t* index, int32_t dim,	
	int32_t var, int32_t nentries,	
	int32-t $*$ entries,	
	double* values,	
	sidl_BaseInterface *_ex)	
	Add to matrix coefficients index by index	27
157	· ·	
1.5.7	$\mathrm{int}32$ _t	

	${f bHYPRE_SStructMatrixView_AddToBoxValues}$ (
	bHYPRE_SStructMatrixView	
	self, int32_t part,	
	int32_t* ilower,	
	int32.t* iupper,	
	int32_t dim, int32_t var,	
	int32_t nentries,	
	int32_t* entries,	
	double* values,	
	int32_t nvalues,	
	sidl_BaseInterface *_ex)	
	Add to matrix coefficients a box at a time	27
1.5.8	SIDL_C_INLINE_DECL int32_t	
	${\bf bHYPRE_SStructMatrixView_SetSymmetric}\ ($	
	bHYPRE_SStructMatrixView	
	$self, int 32_t part,$	
	int32_t var, int32_t to_var,	
	int32_t symmetric,	
	sidl_BaseInterface *_ex)	
	Define symmetry properties for the stencil entries in the matrix	28
	SIDL_C_INLINE_DECL int32_t	20
	bHYPRE_SStructMatrixView_SetNSSymmetric (
	bHYPRE_SStructMatrixView	
	self, int32_t symmetric,	
	sidl_BaseInterface *_ex)	
	Define symmetry properties for all non-stencil matrix entries	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructMatrixView_SetComplex (bHYPRE_SStructMatrixView	
	self, sidl_BaseInterface *_ex)	
	Set the matrix to be complex	
1.5.9	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructMatrixView_Print (bHYPRE_SStructMatrixView self,	
	const char* filename, int32_t all,	
	sidl_BaseInterface *_ex)	
	Print the matrix to file	28
	_ex	
	Cast method for interface and class type conversions	
	void*	
	bHYPRE_SStructMatrixViewcast2 (void* obj, const char* type,	
	sidl_BaseInterface *_ex)	
	String cast method for interface and class type conversions	
	SIDL_C_INLINE_DECL void	
	bHYPRE_SStructMatrixView_exec (bHYPRE_SStructMatrixView self,	
	const char* methodName,	
	sidl_rmi_Call inArgs,	
	sidl_rmi_Return outArgs,	
	sidl_BaseInterface *_ex) Select and execute a method by name	
	SIDL_C_INLINE_DECL_char*	

 $\label{eq:bhypre_sstructMatrixView_getURL} \ (\ \ \ \ \ \ \, \text{bhypre_sstructMatrixView self,} \\ \text{sidl_BaseInterface *_ex})$

Get the URL of the Implementation of this object (for RMI)

SIDL_C_INLINE_DECL void

bHYPRE_SStructMatrixView__raddRef (bHYPRE_SStructMatrixView self, sidl_BaseInterface *_ex)

On a remote object, addrefs the remote instance

SIDL_C_INLINE_DECL sidl_bool

bHYPRE_SStructMatrixView__isRemote (bHYPRE_SStructMatrixView self, sidl_BaseInterface *_ex)

 $TRUE\ if\ this\ object\ is\ remote,\ false\ if\ local$

 $sidl_bool$

bHYPRE_SStructMatrixView__isLocal (bHYPRE_SStructMatrixView self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

 $**_{-}ex$

Cast method for interface and class type conversions

1.5.10 **_ex

RMI connector function for the class

1.5.1

struct bHYPRE_SStructMatrixView_object

Symbol "bHYPRE.SStructMatrixView" (version 1.0.0)

1.5.2

extern C bHYPRE_SStructMatrixView bHYPRE_SStructMatrixView_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

1.5.3

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrixView_SetGraph (bHYPRE_SStructMatrixView self, bHYPRE_SStructGraph graph, sidl_BaseInterface *_ex)

Set the matrix graph. DEPRECATED Use Create

1.5.4

$int32_t$

bHYPRE_SStructMatrixView_SetValues (bHYPRE_SStructMatrixView self, int32_t part, int32_t* index, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, sidl_BaseInterface *_ex)

Set matrix coefficients index by index.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type (there are no such restrictions for non-stencil entries).

If the matrix is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

1.5.5

$int32_t$

bHYPRE_SStructMatrixView_SetBoxValues (bHYPRE_SStructMatrixView self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set matrix coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type (there are no such restrictions for non-stencil entries).

If the matrix is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

1.5.6

int32 t

bHYPRE_SStructMatrixView_AddToValues (bHYPRE_SStructMatrixView self, int32_t part, int32_t* index, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, sidl_BaseInterface *_ex)

Add to matrix coefficients index by index.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type.

If the matrix is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

1.5.7

int32_t

bHYPRE_SStructMatrixView_AddToBoxValues (

bHYPRE_SStructMatrixView self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, int32_t neutries, sidl_BaseInterface *_ex)

Add to matrix coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of stencil type. Also, they must all represent couplings to the same variable type.

If the matrix is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

1.5.8

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrixView_SetSymmetric (bHYPRE_SStructMatrixView self, int32_t part, int32_t var, int32_t to_var, int32_t symmetric, sidl_BaseInterface *_ex)

Define symmetry properties for the stencil entries in the matrix. The boolean argument symmetric is applied to stencil entries on part part that couple variable var to variable to_var. A value of -1 may be used for part, var, or to_var to specify "all". For example, if part and to_var are set to -1, then the boolean is applied to stencil entries on all parts that couple variable var to all other variables.

By default, matrices are assumed to be nonsymmetric. Significant storage savings can be made if the matrix is symmetric.

1.5.9

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrixView_Print (bHYPRE_SStructMatrixView self, const char* filename, int32_t all, sidl_BaseInterface *_ex)

Print the matrix to file. This is mainly for debugging purposes.

_ 1.5.10 _

struct bHYPRE_SStructMatrixView__object* bHYPRE_SStructMatrixView__connectI const char * url sidl_bool ar struct sidl_BaseInterface__object **_ex

RMI connector function for the class. (no addref)

_ 1.6 _____

SemiStructured Vector View

Names

1.6.1 struct bHYPRE_SStructVectorView_object

	Symbol "bHYPRE
1.6.2	extern C bHYPRE_SStructVectorView
	bHYPRE_SStructVectorViewconnect (const char *,
	sidl_BaseInterface *_ex)
	RMI connector function for the class
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVectorView_SetGrid (bHYPRE_SStructVectorView self, bHYPRE_SStructGrid grid, sidl_BaseInterface *_ex)
	Set the vector grid
.6.3	SIDL_C_INLINE_DECL int32_t
	bHYPRE_SStructVectorView_SetValues (bHYPRE_SStructVectorView self, int32_t part, int32_t* index, int32_t dim, int32_t var, double value, sidl_BaseInterface *_ex) Set vector coefficients index by index
	· ·
1.6.4	int32_t
	bHYPRE_SStructVectorView_SetBoxValues (bHYPRE_SStructVectorView
	self, int32_t part,
	int32_t* ilower,
	int32_t* iupper, int32_t dim,
	int32_t var, double* values,
	$int32_{-}t$ nvalues,
	sidl_BaseInterface *_ex)
	Set vector coefficients a box at a time
.6.5	SIDL_C_INLINE_DECL int32_t
	bHYPRE_SStructVectorView_AddToValues (bHYPRE_SStructVectorView
	self, int32_t part,
	int32_t* index, int32_t dim,
	int32_t var, double value,
	sidl_BaseInterface *_ex)
	Set vector coefficients index by index
.6.6	int32_t
	bHYPRE_SStructVectorView_AddToBoxValues (
	bHYPRE_SStructVectorView
	$\begin{array}{c} \text{self,} & \text{int} 32_\text{t part,} \\ \text{int} 32_\text{t}^* & \text{ilower,} \end{array}$
	int32_t* inower,
	int32_t dim, int32_t var,
	double* values,
	int32_t nvalues,
	sidl_BaseInterface *_ex)
	Set vector coefficients a box at a time
	SIDL_C_INLINE_DECL int32_t
	$\mathbf{bHYPRE_SStructVectorView_Gather} \ (\ \ \mathbf{bHYPRE_SStructVectorView} \ \mathbf{self},$
	sidl_BaseInterface *_ex)
	$Gather\ vector\ data\ before\ calling\ { t GetValues}$
.6.7	SIDL_C_INLINE_DECL int32_t

	$\mathbf{bHYPRE_SStructVectorView_GetValues} \ (\ \ \mathbf{bHYPRE_SStructVectorView}$	
	self, int32_t part,	
	$int32_t*index, int32_t dim,$	
	int32 _t var, double* value,	
	sidl_BaseInterface *_ex)	
	Get vector coefficients index by index	33
1.6.8	$\mathrm{int}32$ _t	
	${\bf bHYPRE_SStructVectorView_GetBoxValues} \ ($	
	bHYPRE_SStructVectorView	
	$\mathrm{self}, \mathrm{int} 32$ _t part,	
	int32_t* ilower,	
	int32_t* iupper, int32_t dim,	
	int32_t var, double* values,	
	int32_t nvalues, sidl_BaseInterface *_ex)	
	Get vector coefficients a box at a time	33
	•	55
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructVectorView_SetComplex (bHYPRE_SStructVectorView self, sidl_BaseInterface *_ex)	
	Set the vector to be complex	
1.00	•	
1.6.9	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVectorView_Print (bHYPRE_SStructVectorView self,	
	const char* filename, int32_t all,	
	sidl_BaseInterface *_ex)	
	Print the vector to file	34
	OV	
	_ex Cast method for interface and class type conversions	
	void*	
	bHYPRE_SStructVectorViewcast2 (void* obj, const char* type, sidl_BaseInterface *_ex)	
	String cast method for interface and class type conversions	
	· · · · · · · · · · · · · · · · · · ·	
	SIDL_C_INLINE_DECL void	
	bHYPRE_SStructVectorView_exec (bHYPRE_SStructVectorView self, const char* methodName,	
	sidl_rmi_Call inArgs,	
	sidl_rmi_Return outArgs,	
	sidl_BaseInterface *_ex)	
	Select and execute a method by name	
	SIDL_C_INLINE_DECL_char*	
	bHYPRE_SStructVectorViewgetURL (bHYPRE_SStructVectorView self,	
	sidl_BaseInterface *_ex)	
	Get the URL of the Implementation of this object (for RMI)	
	SIDL_C_INLINE_DECL_void	
	bHYPRE_SStructVectorView_raddRef (bHYPRE_SStructVectorView self,	
	sidl_BaseInterface *_ex)	
	On a remote object, addrefs the remote instance	
	SIDL_C_INLINE_DECL_sidl_bool	

bHYPRE_SStructVectorView__isRemote (bHYPRE_SStructVectorView self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

sidl_bool

bHYPRE_SStructVectorView__isLocal (bHYPRE_SStructVectorView self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

 $**_{-}ex$

Cast method for interface and class type conversions

1.6.10 **_ex

RMI connector function for the class

1.6.1 _

struct bHYPRE_SStructVectorView_object

Symbol "bHYPRE.SStructVectorView" (version 1.0.0)

_ 1.6.2 _

extern C bHYPRE_SStructVectorView bHYPRE_SStructVectorView_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

 $_{-}$ 1.6.3 $_{-}$

SIDL_C_INLINE_DECL int32_t

bHYPRE_SStructVectorView_SetValues (bHYPRE_SStructVectorView self, int32_t part, int32_t* index, int32_t dim, int32_t var, double value, sidl_BaseInterface *_ex)

Set vector coefficients index by index.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

If the vector is complex, then value consists of a pair of doubles representing the real and imaginary parts of the complex value.

1.6.4

$int32_t$

bHYPRE_SStructVectorView_SetBoxValues (bHYPRE_SStructVectorView self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set vector coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

If the vector is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

1.6.5

SIDL_C_INLINE_DECL int32_t

bHYPRE_SStructVectorView_AddToValues (bHYPRE_SStructVectorView self, int32_t part, int32_t* index, int32_t dim, int32_t var, double value, sidl_BaseInterface *_ex)

Set vector coefficients index by index.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

If the vector is complex, then value consists of a pair of doubles representing the real and imaginary parts of the complex value.

1.6.6

$int32_t$

bHYPRE_SStructVectorView_AddToBoxValues (

bHYPRE_SStructVectorView self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set vector coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

If the vector is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

1.6.7

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVectorView_GetValues (bHYPRE_SStructVectorView self, int32_t part, int32_t* index, int32_t dim, int32_t var, double* value, sidl_BaseInterface *_ex)

Get vector coefficients index by index.

NOTE: Users may only get values on processes that own the associated variables.

If the vector is complex, then value consists of a pair of doubles representing the real and imaginary parts of the complex value.

1.6.8

int32_t bHYPRE_SStructVectorView_GetBoxValues (bHYPRE_SStructVectorView self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Get vector coefficients a box at a time.

NOTE: Users may only get values on processes that own the associated variables.

If the vector is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

1.6.9

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVectorView_Print (bHYPRE_SStructVectorView self, const char* filename, int32_t all, sidl_BaseInterface *_ex)

Print the vector to file. This is mainly for debugging purposes.

1.6.10

struct bHYPRE_SStructVectorView__object* bHYPRE_SStructVectorView__connectI const char * url sidl_bool ar struct sidl_BaseInterface__object **_ex

RMI connector function for the class. (no addref)

 $\mathbf{2}$

Operator Interface

Names		
2.1	struct bHYPRE_Operator_object Symbol "bHYPRE	37
2.2	extern C bHYPRE_Operator bHYPRE_Operator_connect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	38
2.3	SIDL_C_INLINE_DECL_int32_t bHYPRE_Operator_SetCommunicator (bHYPRE_Operator self,	
	Set the MPI Communicator	38
2.4	SIDL_C_INLINE_DECL void bHYPRE_Operator_Destroy (bHYPRE_Operator self,	38
	SIDL_C_INLINE_DECL_int32_t bHYPRE_Operator_SetIntParameter (bHYPRE_Operator self,	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_Operator_SetDoubleParameter (bHYPRE_Operator self,	
	SIDL_C_INLINE_DECL int32_t bHYPRE_Operator_SetStringParameter (bHYPRE_Operator self, const char* name, const char* value, sidl_BaseInterface *_ex)	
	Set the string parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_Operator_SetIntArray1Parameter (bHYPRE_Operator self,	
	Set the int 1-D array parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_Operator_SetIntArray2Parameter ( bHYPRE_Operator self,
                                               const char* name,
                                              struct sidl_int_array* value,
                                              sidl_BaseInterface *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Operator_SetDoubleArray1Parameter ( bHYPRE_Operator self,
                                                   const char* name,
                                                   double* value,
                                                   int32_t nvalues.
                                                   sidl_BaseInterface *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_Operator_SetDoubleArray2Parameter ( bHYPRE_Operator self,
                                                   const char* name,
                                                   struct sidl_double_array*
                                                   value,
                                                   sidl_BaseInterface *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Operator_GetIntValue ( bHYPRE_Operator self,
                                   const char* name, int32_t* value,
                                   sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_Operator_GetDoubleValue ( bHYPRE_Operator self,
                                       const char* name, double* value,
                                       sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Operator_Setup ( bHYPRE_Operator self, bHYPRE_Vector b,
                            bHYPRE_Vector x, sidl_BaseInterface *_ex)
      (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_Operator_Apply (bHYPRE_Operator self, bHYPRE_Vector b,
                            bHYPRE_Vector* x, sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_Operator_ApplyAdjoint ( bHYPRE_Operator self,
                                    bHYPRE_Vector b,
                                    bHYPRE_Vector* x,
                                    sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_ex
      Cast method for interface and class type conversions
void*
```

```
bHYPRE_Operator_cast2 (void* obj, const char* type,
                                        sidl_BaseInterface *_ex)
                   String cast method for interface and class type conversions
            SIDL_C_INLINE_DECL_void
            bHYPRE_Operator_exec ( bHYPRE_Operator self,
                                        const char* methodName, sidl_rmi_Call inArgs,
                                       sidl_rmi_Return outArgs, sidl_BaseInterface *_ex)
                   Select and execute a method by name
            SIDL_C_INLINE_DECL_char*
            bHYPRE_Operator__getURL ( bHYPRE_Operator self,
                                           sidl_BaseInterface *_ex)
                   Get the URL of the Implementation of this object (for RMI)
            SIDL_C_INLINE_DECL void
            bHYPRE_Operator_raddRef ( bHYPRE_Operator self,
                                           sidl_BaseInterface *_ex)
                   On a remote object, addrefs the remote instance
            SIDL_C_INLINE_DECL sidl_bool
            bHYPRE_Operator__isRemote ( bHYPRE_Operator self,
                                             sidl_BaseInterface *_ex)
                   TRUE if this object is remote, false if local
            sidl_bool
            bHYPRE_Operator__isLocal ( bHYPRE_Operator self,
                                          sidl_BaseInterface *_ex)
                   TRUE if this object is remote, false if local
            **_ex
                   Cast method for interface and class type conversions
2.5
            **_ex
                   RMI connector function for the class .....
                                                                                             38
```

2.1

struct bHYPRE_Operator_object

Symbol "bHYPRE.Operator" (version 1.0.0)

An Operator is anything that maps one Vector to another. The terms Setup and Apply are reserved for Operators. The implementation is allowed to assume that supplied parameter arrays will not be destroyed.

_ 2.2 .

extern C bHYPRE_Operator **bHYPRE_Operator__connect** (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

_ 2.3 _

SIDL_C_INLINE_DECL int32_t bHYPRE_Operator_SetCommunicator (bHYPRE_Operator self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

2.4

SIDL_C_INLINE_DECL_void bHYPRE_Operator_Destroy (bHYPRE_Operator_self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

_ 2.5 _

RMI connector function for the class. (no addref)

3

Vector Interface

Names		
3.1	struct bHYPRE_Vector_object Symbol "bHYPRE	40
3.2	extern C bHYPRE_Vector bHYPRE_Vector_connect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	40
	SIDL_C_INLINE_DECL int32_t bHYPRE_Vector_Clear (bHYPRE_Vector self, sidl_BaseInterface *_ex) Set self to 0	
	SIDL_C_INLINE_DECL int32_t bHYPRE_Vector_Copy (bHYPRE_Vector self, bHYPRE_Vector x,	
3.3	SIDL_C_INLINE_DECL int32_t bHYPRE_Vector_Clone (bHYPRE_Vector self, bHYPRE_Vector* x,	40
	SIDL_C_INLINE_DECL int32_t bHYPRE_Vector_Scale (bHYPRE_Vector self, double a, sidl_BaseInterface *_ex) Scale self by a	
	SIDL_C_INLINE_DECL int32_t bHYPRE_Vector_Dot (bHYPRE_Vector self, bHYPRE_Vector x, double* d, sidl_BaseInterface *_ex) Compute d, the inner-product of self and x	
	SIDL_C_INLINE_DECL int32_t bHYPRE_Vector_Axpy (bHYPRE_Vector self, double a,	
	_ex Cast method for interface and class type conversions	
	void* bHYPRE_Vectorcast2 (void* obj, const char* type, sidl_BaseInterface *_ex) String cast method for interface and class type conversions	
	SIDL_C_INLINE_DECL_void bHYPRE_Vector_exec (bHYPRE_Vector self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex) Select and execute a method by name	
	SIDL_C_INLINE_DECL_char*	

bHYPRE_Vector_getURL (bHYPRE_Vector self, sidl_BaseInterface *_ex) Get the URL of the Implementation of this object (for RMI) SIDL_C_INLINE_DECL void bHYPRE_Vector_raddRef (bHYPRE_Vector self, sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance SIDL_C_INLINE_DECL sidl_bool bHYPRE_Vector_isRemote (bHYPRE_Vector self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local $sidl_bool$ bHYPRE_Vector_isLocal (bHYPRE_Vector self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local $**_ex$ Cast method for interface and class type conversions **_ex 3.4 RMI connector function for the class 41

3.1

struct bHYPRE_Vector_object

Symbol "bHYPRE.Vector" (version 1.0.0)

3.2 .

extern C bHYPRE_Vector bHYPRE_Vector_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

_ 3.3 _

SIDL_C_INLINE_DECL int32_t bHYPRE_Vector_Clone (bHYPRE_Vector self, bHYPRE_Vector* x, sidl_BaseInterface *_ex)

Create an x compatible with self. The new vector's data is not specified.

NOTE: When this method is used in an inherited class, the cloned Vector object can be cast to an object with the inherited class type.

3 4

RMI connector function for the class. (no addref)

Matrices and Vectors

Names 4.1	IJParCSR Matrix	
		42
4.2	IJParCSR Vector	۲,
4.3	Struct Matrix	53
		59
4.4	Struct Vector	68
4.5	SemiStructured Matrix	75
4.6	SemiStructured Vector	85
4.7	SemiStructured ParCSR Matrix	0.6
4.8	SemiStructured ParCSR Vector	92
		103

4.1

IJParCSR Matrix

Names

_ex

Constructor function for the class

 $bHYPRE_IJParCSRMatrix$

 $\mathbf{bHYPRE_IJParCSRMatrix_createRemote} \ (\mathbf{const} \ \mathbf{char} \ ^* \ \mathbf{url},$

sidl_BaseInterface *_ex)

RMI constructor function for the class

 $b HYPRE_IJParCSRMatrix$

bHYPRE_IJParCSRMatrix_wrapObj (void * data, sidl_BaseInterface *_ex)

Wraps up the private data struct pointer (struct
bHYPRE_IJParCSRMatrix_data) passed in rather than running the

constructor

4.1.2 bHYPRE_IJParCSRMatrix

	bHYPRE_IJParCSRMatrix_connect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	48
	bHYPRE_IJParCSRMatrix	
	bHYPRE_IJParCSRMatrix_Create (bHYPRE_MPICommunicator	
	mpi_comm, int32_t ilower,	
	int32_t iupper, int32_t jlower,	
	int32_t jupper, sidl_BaseInterface *_ex)	
	This function is the preferred way to create an IJParCSR Matrix	
	bHYPRE_IJParCSRMatrix	
	bHYPRE_IJParCSRMatrix_GenerateLaplacian (
	bHYPRE_MPICommunicator	
	mpi_comm, int32_t nx,	
	int32_t ny, int32_t nz,	
	$int32_{-}t Px$, $int32_{-}t Py$,	
	$int32_{-}t Pz$, $int32_{-}t p$,	
	$int32_{-}t q$, $int32_{-}t r$,	
	double* values,	
	$int32_{-t}$ nvalues,	
	int32_t discretization,	
	sidl_BaseInterface *_ex)	
	$Method: \ Generate Laplacian[]$	
4.1.3	int32_t bHYPRE_IJParCSRMatrix_SetDiagOffdSizes (bHYPRE_IJParCSRMatrix self, int32_t* diag_sizes, int32_t* offdiag_sizes, int32_t local_nrows, sidl_BaseInterface *_ex)	
	(Optional) Set the max number of nonzeros to expect in each row of the diagonal and off-diagonal blocks	49
4.1.4	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_IJParCSRMatrix_SetLocalRange (bHYPRE_IJParCSRMatrix	
	self, int32_t ilower,	
	int32_t iupper, int32_t jlower,	
	$int32_{-}t$ jupper,	
	sidl_BaseInterface *_ex)	
	Set the local range for a matrix object	49
4.1.5	$\mathrm{int}32$ _{t}	
	bHYPRE_IJParCSRMatrix_SetValues (bHYPRE_IJParCSRMatrix self, int32_t nrows, int32_t* ncols, int32_t* rows, int32_t* cols, double* values, int32_t nnonzeros,	
	sidl-BaseInterface *_ex)	
	Sets values for nrows of the matrix	49
116		
4.1.6	$\mathrm{int}32_{-}\mathrm{t}$	

	$\mathbf{bHYPRE_IJParCSRMatrix_AddToValues} \ (\ \ \mathbf{bHYPRE_IJParCSRMatrix}$	
	self, int32_t nrows,	
	$int32_t* ncols$, $int32_t* rows$,	
	int32_t* cols, double* values,	
	int32_t nnonzeros,	
	sidl_BaseInterface *_ex)	
	Adds to values for nrows of the matrix	50
	SIDL_C_INLINE_DECL int32_t	
	$\mathbf{bHYPRE_IJParCSRMatrix_GetLocalRange} \ (\ \ \mathbf{bHYPRE_IJParCSRMatrix}$	
	self, $int32_t^*$ ilower,	
	$int32_{-}t^{*}$ iupper,	
	$int32_{-}t^{*}$ jlower,	
	$int32_{-}t^{*}$ jupper,	
	sidl_BaseInterface *_ex)	
	Gets range of rows owned by this processor and range of column partitioning for this processor	
	$\mathrm{int}32$ _t	
	bHYPRE_IJParCSRMatrix_GetRowCounts (bHYPRE_IJParCSRMatrix	
	self, int32_t nrows,	
	$int32_{-}t^* rows$, $int32_{-}t^* ncols$,	
	sidl_BaseInterface *_ex)	
	Gets number of nonzeros elements for nrows rows specified in rows and returns them in ncols, which needs to be allocated by the user	
4.1.7	$\mathrm{int}32$ _t	
1.1.1	bHYPRE_IJParCSRMatrix_GetValues (bHYPRE_IJParCSRMatrix self,	
	int32_t nrows, int32_t* ncols,	
	$int32t^* rows, int32t^* cols,$	
	double* values, int32_t nnonzeros,	
	sidl_BaseInterface *_ex)	
	Gets values for nrows rows or partial rows of the matrix	50
4.1.8	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_IJParCSRMatrix_SetRowSizes (bHYPRE_IJParCSRMatrix self,	
	int32_t* sizes, int32_t nrows,	
	sidl_BaseInterface *_ex)	
	(Optional) Set the max number of nonzeros to expect in each row	50
4.1.9	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_IJParCSRMatrix_Print (bHYPRE_IJParCSRMatrix self,	
	const char* filename,	
	sidl_BaseInterface *_ex)	
	Print the matrix to file	51
4.1.10	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_IJParCSRMatrix_Read (bHYPRE_IJParCSRMatrix self,	
	const char* filename,	
	bHYPRE_MPICommunicator comm,	
	sidl_BaseInterface *_ex)	
	Read the matrix from file	51
4.1.11	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_IJParCSRMatrix_SetCommunicator (
	bHYPRE_IJParCSRMatrix	
	$\operatorname{self},$	
	bHYPRE_MPICommunicator	
	mpi_comm,	
	sidl_BaseInterface *_ex) Set the MPI Communicator	51
		91
4.1.12	SIDL_C_INLINE_DECL_void	
	bHYPRE_IJParCSRMatrix_Destroy (bHYPRE_IJParCSRMatrix self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	52
		Ŭ -
	SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRMatrix_Initialize (bHYPRE_IJParCSRMatrix self,	
	sidl_BaseInterface *_ex)	
	Prepare an object for setting coefficient values, whether for the first time or	
	subsequently	
4.1.13	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_IJParCSRMatrix_Assemble (bHYPRE_IJParCSRMatrix self,	
	sidl_BaseInterface *_ex)	
	Finalize the construction of an object before using, either for the first time	
	or on subsequent uses	52
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_IJParCSRMatrix_SetIntParameter (bHYPRE_IJParCSRMatrix	
	self, const char* name, int 32_{-} t value,	
	sidl_BaseInterface *_ex)	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_IJParCSRMatrix_SetDoubleParameter (
	bHYPRE_IJParCSRMatrix	
	self, const char* name,	
	double value,	
	sidl_BaseInterface *_ex)	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_IJParCSRMatrix_SetStringParameter (
	bHYPRE_IJParCSRMatrix self, const char* name,	
	const char* value,	
	sidl_BaseInterface *_ex)	
	Set the string parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_IJParCSRMatrix_SetIntArray1Parameter (
                                                       bHYPRE_IJParCSRMatrix
                                                       const char* name,
                                                       int32_t* value,
                                                       int32_t nvalues,
                                                       sidl_BaseInterface
                                                       *_ex)
      Set the int 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_IJParCSRMatrix_SetIntArray2Parameter (
                                                       bHYPRE_IJParCSRMatrix
                                                       self,
                                                       const char* name,
                                                       struct
                                                       sidl_int_array*
                                                       value,
                                                       sidl_BaseInterface
                                                       *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_IJParCSRMatrix_SetDoubleArray1Parameter (
                                                           bHYPRE_IJParCSRMatrix
                                                           self, const
                                                           char* name,
                                                           double* value,
                                                           int32_t nvalues.
                                                           sidl\_BaseInterface
                                                            *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE\_IJParCSRMatrix\_SetDoubleArray2Parameter\ (
                                                           bHYPRE_IJParCSRMatrix
                                                           self, const
                                                           char* name,
                                                           struct
                                                           sidl_double_array*
                                                           value,
                                                           sidl_BaseInterface
                                                            *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_IJParCSRMatrix_GetIntValue ( bHYPRE_IJParCSRMatrix self,
                                           const char* name.
                                           int32_t* value,
                                           sidl_BaseInterface *_ex)
      Set the int parameter associated with name
```

SIDL_C_INLINE_DECL int32_t

bHYPRE_IJParCSRMatrix_GetDoubleValue (bHYPRE_IJParCSRMatrix

```
self, const char* name,
                                                          double* value.
                                                          sidl_BaseInterface *_ex)
                  Get the double parameter associated with name
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_IJParCSRMatrix_Setup ( bHYPRE_IJParCSRMatrix self,
                                               bHYPRE_Vector b, bHYPRE_Vector x,
                                               sidl_BaseInterface *_ex)
                  (Optional) Do any preprocessing that may be necessary in order to execute
                  Apply
            SIDL_C_INLINE_DECL_int32_t
            bHYPRE_IJParCSRMatrix_Apply ( bHYPRE_IJParCSRMatrix self,
                                                bHYPRE_Vector b.
                                                bHYPRE_Vector* x,
                                                sidl_BaseInterface *_ex)
                  Apply the operator to b, returning x
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_IJParCSRMatrix_ApplyAdjoint ( bHYPRE_IJParCSRMatrix
                                                       self, bHYPRE_Vector b,
                                                       bHYPRE_Vector* x,
                                                       sidl_BaseInterface *_ex)
                  Apply the adjoint of the operator to b, returning x
            SIDL_C_INLINE_DECL int32_t
4.1.14
            bHYPRE_IJParCSRMatrix_GetRow ( bHYPRE_IJParCSRMatrix self,
                                                  int32_t row, int32_t* size,
                                                  struct sidl_int_array** col_ind,
                                                  struct sidl_double_array** values,
                                                  sidl_BaseInterface *_ex)
                  The GetRow method will allocate space for its two output arrays on the first
                  call .....
                                                                                           52
            _{-}ex
                  Cast method for interface and class type conversions
            *void
            bHYPRE_IJParCSRMatrix_cast2 (void* obj, const char* type,
                                               sidl_BaseInterface *_ex)
                  String cast method for interface and class type conversions
            SIDL_C_INLINE_DECL void
            bHYPRE_IJParCSRMatrix_exec ( bHYPRE_IJParCSRMatrix self,
                                               const char* methodName,
                                               sidl_rmi_Call inArgs,
                                               sidl_rmi_Return outArgs,
                                               sidl_BaseInterface *_ex)
                  Select and execute a method by name
            SIDL_C_INLINE_DECL char*
            bHYPRE_IJParCSRMatrix__getURL ( bHYPRE_IJParCSRMatrix self,
                                                  sidl_BaseInterface *_ex)
                  Get the URL of the Implementation of this object (for RMI)
            SIDL_C_INLINE_DECL_void
```

bHYPRE_IJParCSRMatrix_raddRef (bHYPRE_IJParCSRMatrix self, sidl_BaseInterface *_ex)

On a remote object, addrefs the remote instance

SIDL_C_INLINE_DECL_sidl_bool

bHYPRE_IJParCSRMatrix_isRemote (bHYPRE_IJParCSRMatrix self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

 $sidl_bool$

bHYPRE_IJParCSRMatrix__isLocal (bHYPRE_IJParCSRMatrix self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

**_ex

Cast method for interface and class type conversions

4.1.15 **_**ex**

RMI connector function for the class

4.1.1

struct bHYPRE_IJParCSRMatrix_object

Symbol "bHYPRE.IJParCSRMatrix" (version 1.0.0)

The IJParCSR matrix class.

Objects of this type can be cast to IJMatrixView, Operator, or CoefficientAccess objects using the <code>__cast</code> methods.

4.1.2

bHYPRE_IJParCSRMatrix bHYPRE_IJParCSRMatrix_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

52

4.1.3

 $int32_t$

bHYPRE_IJParCSRMatrix_SetDiagOffdSizes (bHYPRE_IJParCSRMatrix self, int32_t* diag_sizes, int32_t* offdiag_sizes, int32_t local_nrows, sidl_BaseInterface *_ex)

(Optional) Set the max number of nonzeros to expect in each row of the diagonal and off-diagonal blocks. The diagonal block is the submatrix whose column numbers correspond to rows owned by this process, and the off-diagonal block is everything else. The arrays diag_sizes and offdiag_sizes contain estimated sizes for each row of the diagonal and off-diagonal blocks, respectively. This routine can significantly improve the efficiency of matrix construction, and should always be utilized if possible.

Not collective.

4.1.4

SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRMatrix_SetLocalRange (bHYPRE_IJParCSRMatrix self, int32_t ilower, int32_t ilower, int32_t jlower, int32_t jupper, sidl_BaseInterface *_ex)

Set the local range for a matrix object. Each process owns some unique consecutive range of rows, indicated by the global row indices ilower and iupper. The row data is required to be such that the value of ilower on any process p be exactly one more than the value of iupper on process p-1. Note that the first row of the global matrix may start with any integer value. In particular, one may use zero- or one-based indexing.

For square matrices, jlower and jupper typically should match ilower and iupper, respectively. For rectangular matrices, jlower and jupper should define a partitioning of the columns. This partitioning must be used for any vector v that will be used in matrix-vector products with the rectangular matrix. The matrix data structure may use jlower and jupper to store the diagonal blocks (rectangular in general) of the matrix separately from the rest of the matrix.

Collective.

$_{-}$ 4.1.5 $_{-}$

 $int32_t$

bHYPRE_IJParCSRMatrix_SetValues (bHYPRE_IJParCSRMatrix self, int32_t nrows, int32_t* ncols, int32_t* rows, int32_t* cols, double* values, int32_t nnonzeros, sidl_BaseInterface *_ex)

Sets values for nrows of the matrix. The arrays ncols and rows are of dimension nrows and contain the number of columns in each row and the row indices, respectively. The array cols contains the column indices for each of the rows, and is ordered by rows. The data in the values array corresponds directly to the column entries in cols. The last argument is the size of the cols and values arrays, i.e. the total number of nonzeros being provided, i.e. the sum of all values in ncols. This functin erases any previous values at the specified locations and replaces them with new ones, or, if there was no value there before, inserts a new one.

Not collective.

4.1.6

 $int32_t$

bHYPRE_IJParCSRMatrix_AddToValues (bHYPRE_IJParCSRMatrix self, int32_t nrows, int32_t* ncols, int32_t* cols, double* values, int32_t nnonzeros, sidl_BaseInterface *_ex)

Adds to values for **nrows** of the matrix. Usage details are analogous to **SetValues**. Adds to any previous values at the specified locations, or, if there was no value there before, inserts a new one.

Not collective.

4.1.7

 $int32_t$

bHYPRE_IJParCSRMatrix_GetValues (bHYPRE_IJParCSRMatrix self, int32_t nrows, int32_t* ncols, int32_t* rows, int32_t* cols, double* values, int32_t nnonzeros, sidl_BaseInterface *_ex)

Gets values for nrows rows or partial rows of the matrix. Usage details are analogous to SetValues.

4.1.8

SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRMatrix_SetRowSizes (bHYPRE_IJParCSRMatrix self, int32_t* sizes, int32_t nrows, sidl_BaseInterface *_ex)

(Optional) Set the max number of nonzeros to expect in each row. The array sizes contains estimated sizes for each row on this process. The integer nrows is the number of rows in the local matrix. This call can significantly improve the efficiency of matrix construction, and should always be utilized if possible.

Not collective.

4.1.9

SIDL_C_INLINE_DECL int32_t **bHYPRE_IJParCSRMatrix_Print** (bHYPRE_IJParCSRMatrix self, const char* filename, sidl_BaseInterface *_ex)

Print the matrix to file. This is mainly for debugging purposes.

__ 4.1.10 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRMatrix_Read (bHYPRE_IJParCSRMatrix self, const char* filename, bHYPRE_MPICommunicator comm, sidl_BaseInterface *_ex)

Read the matrix from file. This is mainly for debugging purposes.

4.1.11

SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRMatrix_SetCommunicator (bHYPRE_IJParCSRMatrix self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, Use Create()

4.1.12

SIDL_C_INLINE_DECL_void bHYPRE_IJParCSRMatrix_Destroy (bHYPRE_IJParCSRMatrix self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

4.1.13

SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRMatrix_Assemble (bHYPRE_IJParCSRMatrix self, sidl_BaseInterface *_ex)

Finalize the construction of an object before using, either for the first time or on subsequent uses. Initialize and Assemble always appear in a matched set, with Initialize preceding Assemble. Values can only be set in between a call to Initialize and Assemble.

4.1.14

SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRMatrix_GetRow (bHYPRE_IJParCSRMatrix self, int32_t row, int32_t* size, struct sidl_int__array** col_ind, struct sidl_double_array** values, sidl_BaseInterface *_ex)

The GetRow method will allocate space for its two output arrays on the first call. The space will be reused on subsequent calls. Thus the user must not delete them, yet must not depend on the data from GetRow to persist beyond the next GetRow call.

4.1.15

struct bHYPRE_IJParCSRMatrix__object* bHYPRE_IJParCSRMatrix__connectI const char * url sidl_bool ar struct sidl_BaseInterface__object **_ex

 RMI connector function for the class. (no addref)

__ 4.2 _

IJParCSR Vector

Names		
4.2.1	struct bHYPRE_IJParCSRVectorobject Symbol "bHYPRE	56
	_ex Constructor function for the class	
	· ·	
	bHYPRE_IJParCSRVector bHYPRE_IJParCSRVectorcreateRemote (const char * url, sidl_BaseInterface *_ex)	
	RMI constructor function for the class	
	bHYPRE_IJParCSRVector bHYPRE_IJParCSRVectorwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_IJParCSRVectordata) passed in rather than running the constructor	
4.2.2	bHYPRE_IJParCSRVector bHYPRE_IJParCSRVectorconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	56
	bHYPRE_IJParCSRVector bHYPRE_IJParCSRVector_Create (bHYPRE_MPICommunicator	
4.2.3	SIDL_C_INLINE_DECL_int32_t bHYPRE_IJParCSRVector_SetLocalRange (bHYPRE_IJParCSRVector self, int32_t jlower, int32_t jupper, sidl_BaseInterface *_ex)	
	Set the local range for a vector object	56
4.2.4	int32_t bHYPRE_IJParCSRVector_SetValues (bHYPRE_IJParCSRVector self, int32_t nvalues, int32_t* indices, double* values, sidl_BaseInterface *_ex)	
	Sets values in vector	57
4.2.5	$\mathrm{int}32$ _t	

	bHYPRE_IJParCSRVector_AddToValues (bHYPRE_IJParCSRVector self, int32_t nvalues, int32_t* indices, double* values, sidl_BaseInterface *_ex)	
	Adds to values in vector	57
	SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRVector_GetLocalRange (bHYPRE_IJParCSRVector self, int32_t* jlower, int32_t* jupper, sidl_BaseInterface *_ex)	
	Returns range of the part of the vector owned by this processor	
4.2.6	int32_t bHYPRE_IJParCSRVector_GetValues (bHYPRE_IJParCSRVector self,	
	Gets values in vector	57
4.2.7	SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRVector_Print (bHYPRE_IJParCSRVector self,	
	Print the vector to file	58
4.2.8	SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRVector_Read (bHYPRE_IJParCSRVector self,	58
4.2.9	SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRVector_SetCommunicator (bHYPRE_IJParCSRVector self,	
	Set the MPI Communicator	58
4.2.10	SIDL_C_INLINE_DECL_void bHYPRE_IJParCSRVector_Destroy (bHYPRE_IJParCSRVector_self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	58
	SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRVector_Initialize (bHYPRE_IJParCSRVector self, sidl_BaseInterface *_ex)	
	Prepare an object for setting coefficient values, whether for the first time or subsequently	
4.2.11	SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRVector_Assemble (bHYPRE_IJParCSRVector self, sidl_BaseInterface *_ex)	
	Finalize the construction of an object before using, either for the first time or on subsequent uses	59
	SIDL_C_INLINE_DECL_int32_t	

```
bHYPRE_IJParCSRVector_Clear ( bHYPRE_IJParCSRVector self,
                                               sidl_BaseInterface *_ex)
                  Set \ {\tt self} \ to \ \theta
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_IJParCSRVector_Copy ( bHYPRE_IJParCSRVector self,
                                               bHYPRE_Vector x,
                                               sidl_BaseInterface *_ex)
                   Copy data from x into self
4.2.12
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_IJParCSRVector_Clone ( bHYPRE_IJParCSRVector self,
                                               bHYPRE_Vector* x,
                                               sidl_BaseInterface *_ex)
                   Create an x compatible with self .....
                                                                                            59
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_IJParCSRVector_Scale ( bHYPRE_IJParCSRVector self,
                                              double a, sidl_BaseInterface *_ex)
                  Scale  self by a
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_IJParCSRVector_Dot ( bHYPRE_IJParCSRVector self,
                                             bHYPRE_Vector x, double* d,
                                             sidl_BaseInterface *_ex)
                   Compute d, the inner-product of self and x
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_IJParCSRVector_Axpy ( bHYPRE_IJParCSRVector self,
                                               double a, bHYPRE_Vector x,
                                               sidl_BaseInterface *_ex)
                   Add ax to self
            _ex
                   Cast method for interface and class type conversions
            void*
            bHYPRE_IJParCSRVector__cast2 (void* obj, const char* type,
                                               sidl_BaseInterface *_ex)
                  String cast method for interface and class type conversions
            SIDL_C_INLINE_DECL void
            bHYPRE_IJParCSRVector_exec ( bHYPRE_IJParCSRVector self,
                                               const char* methodName,
                                              sidl_rmi_Call inArgs,
                                              sidl_rmi_Return outArgs,
                                              sidl_BaseInterface *_ex)
                  Select and execute a method by name
            SIDL_C_INLINE_DECL char*
            bHYPRE_IJParCSRVector__getURL ( bHYPRE_IJParCSRVector self,
                                                  sidl_BaseInterface *_ex)
                   Get the URL of the Implementation of this object (for RMI)
            SIDL_C_INLINE_DECL_void
            bHYPRE_IJParCSRVector__raddRef ( bHYPRE_IJParCSRVector self,
                                                  sidl_BaseInterface *_ex)
                   On a remote object, addrefs the remote instance
            SIDL_C_INLINE_DECL sidl_bool
```

bHYPRE_IJParCSRVector__isRemote (bHYPRE_IJParCSRVector self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

 $sidl_bool$

bHYPRE_IJParCSRVector__isLocal (bHYPRE_IJParCSRVector self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

 $**_ex$

Cast method for interface and class type conversions

4.2.13 **_ex

4.2.1

struct bHYPRE_IJParCSRVector_object

Symbol "bHYPRE.IJParCSRVector" (version 1.0.0)

The IJParCSR vector class.

Objects of this type can be cast to IJVectorView or Vector objects using the __cast methods.

4.2.2

bHYPRE_IJParCSRVector bHYPRE_IJParCSRVector__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

 $_$ 4.2.3 $_$

SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRVector_SetLocalRange (bHYPRE_IJParCSRVector self, int32_t jlower, int32_t jupper, sidl_BaseInterface *_ex)

Set the local range for a vector object. Each process owns some unique consecutive range of vector unknowns, indicated by the global indices <code>jlower</code> and <code>jupper</code>. The data is required to be such that the value of <code>jlower</code>

on any process p be exactly one more than the value of jupper on process p-1. Note that the first index of the global vector may start with any integer value. In particular, one may use zero- or one-based indexing.

Collective.

 $_{-}$ 4.2.4 $_{-}$

bHYPRE_IJParCSRVector_SetValues (bHYPRE_IJParCSRVector self, int32_t nvalues, int32_t* indices, double* values, sidl_BaseInterface *_ex)

Sets values in vector. The arrays values and indices are of dimension nvalues and contain the vector values to be set and the corresponding global vector indices, respectively. Erases any previous values at the specified locations and replaces them with new ones.

Not collective.

4.2.5

 $int32_t$

 $bHYPRE_IJParCSRVector_AddToValues (bHYPRE_IJParCSRVector self, int 32_t nvalues, int 32_t^* indices, double* values, sidl_BaseInterface *_ex)$

Adds to values in vector. Usage details are analogous to SetValues.

Not collective.

4.2.6

int32_t
bHYPRE_IJParCSRVector_GetValues (bHYPRE_IJParCSRVector self,
int32_t nvalues, int32_t* indices, double* values, sidl_BaseInterface *_ex)

Gets values in vector. Usage details are analogous to SetValues.

Not collective.

4.2.7

SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRVector_Print (bHYPRE_IJParCSRVector self, const char* filename, sidl_BaseInterface *_ex)

Print the vector to file. This is mainly for debugging purposes.

4.2.8

SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRVector_Read (bHYPRE_IJParCSRVector self, const char* filename, bHYPRE_MPICommunicator comm, sidl_BaseInterface *_ex)

Read the vector from file. This is mainly for debugging purposes.

_ 4.2.9 _

SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRVector_SetCommunicator (bHYPRE_IJParCSRVector self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, Use Create()

_ 4.2.10 ____

SIDL_C_INLINE_DECL void bHYPRE_IJParCSRVector_Destroy (bHYPRE_IJParCSRVector self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

4.2.11

SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRVector_Assemble (bHYPRE_IJParCSRVector self, sidl_BaseInterface *_ex)

Finalize the construction of an object before using, either for the first time or on subsequent uses. Initialize and Assemble always appear in a matched set, with Initialize preceding Assemble. Values can only be set in between a call to Initialize and Assemble.

__ 4.2.12 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_IJParCSRVector_Clone (bHYPRE_IJParCSRVector self, bHYPRE_Vector* x, sidl_BaseInterface *_ex)

Create an x compatible with self. The new vector's data is not specified.

NOTE: When this method is used in an inherited class, the cloned Vector object can be cast to an object with the inherited class type.

_ 4.2.13 ___

struct bHYPRE_IJParCSRVector__object* bHYPRE_IJParCSRVector__connectI const char * url sidl_bool ar struct sidl_BaseInterface__object **_ex

RMI connector function for the class. (no addref)

4.3

Struct Matrix

Names

 $_{\mathbf{ex}}$

	Constructor function for the class	
	bHYPRE_StructMatrix	
	bHYPRE_StructMatrixcreateRemote (const char * url,	
	sidl_BaseInterface *_ex)	
	RMI constructor function for the class	
	bHYPRE_StructMatrix	
	bHYPRE_StructMatrix_wrapObj (void * data, sidl_BaseInterface *_ex)	
	Wraps up the private data struct pointer (struct	
	$bHYPRE_StructMatrix__data)$ passed in rather than running the con-	
	structor	
4.3.2	bHYPRE_StructMatrix	
	bHYPRE_StructMatrixconnect (const char *, sidl_BaseInterface *_ex)	
	RMI connector function for the class	6
	bHYPRE_StructMatrix	
	bHYPRE_StructMatrix_Create (bHYPRE_MPICommunicator mpi_comm,	
	bHYPRE_StructGrid grid,	
	bHYPRE_StructStencil stencil,	
	sidl_BaseInterface *_ex)	
	This function is the preferred way to create a Struct Matrix	
4.3.3	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_StructMatrix_SetGrid (bHYPRE_StructMatrix self,	
	bHYPRE_StructGrid grid,	
	sidl_BaseInterface *_ex) Set the grid on which vectors are defined	6
	·	C
4.3.4	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_StructMatrix_SetStencil (bHYPRE_StructMatrix self, bHYPRE_StructStencil stencil,	
	sidl_BaseInterface *_ex)	
	Set the stencil	6
4.3.5		
1.5.5	int32_t bHYPRE_StructMatrix_SetValues (bHYPRE_StructMatrix self,	
	int32_t* index, int32_t dim,	
	int32_t num_stencil_indices,	
	int32_t* stencil_indices, double* values,	
	sidl_BaseInterface *_ex)	
	Set matrix values at grid point, given by "index"	6
4.3.6	$\mathrm{int}32_\mathrm{t}$	
	bHYPRE_StructMatrix_SetBoxValues (bHYPRE_StructMatrix self,	
	int32_t* ilower, int32_t* iupper,	
	$\mathrm{int}32$ _t $\mathrm{dim},$	
	int32_t num_stencil_indices,	
	int32_t* stencil_indices,	
	double* values, int32_t nvalues,	
	sidl_BaseInterface *_ex) Set matrix values throughout a box in the grid, specified by its lower and	
	upper corners specified by its lower and	6
40=	**	Ü
4.3.7	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_StructMatrix_SetNumGhost (bHYPRE_StructMatrix self, int32_t* num_ghost, int32_t dim2, sidl_BaseInterface *_ex)	
	Set the number of ghost zones, separately on the lower and upper sides for each dimension	66
	SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrix_SetSymmetric (bHYPRE_StructMatrix self,	00
	int32_t symmetric, sidl_BaseInterface *_ex)	
	Call SetSymmetric with symmetric=1 to turn on symmetric matrix storage if available	
4.3.8	SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrix_SetConstantEntries (bHYPRE_StructMatrix self,	
	int32_t num_stencil_constant_points, int32_t*	
	stencil_constant_points, sidl_BaseInterface *_ex)	
	State which stencil entries are constant over the grid	66
4.3.9	int32_t bHYPRE_StructMatrix_SetConstantValues (bHYPRE_StructMatrix self, int32_t num_stencil_indices, int32_t* stencil_indices, double* values, sidl_BaseInterface *_ex)	
	Provide values for matrix coefficients which are constant throughout the grid, one value for each stencil point	67
4.3.10	SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrix_SetCommunicator (bHYPRE_StructMatrix self, bHYPRE_MPICommunicator mpi_comm,	
	sidl_BaseInterface *_ex) Set the MPI Communicator	67
4.3.11	SIDL_C_INLINE_DECL_void bHYPRE_StructMatrix_Destroy (bHYPRE_StructMatrix self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	67
	SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrix_Initialize (bHYPRE_StructMatrix self, sidl_BaseInterface *_ex)	
	Prepare an object for setting coefficient values, whether for the first time or subsequently	
4.3.12	SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrix_Assemble (bHYPRE_StructMatrix self, sidl_BaseInterface *_ex)	
	Finalize the construction of an object before using, either for the first time or on subsequent uses	67
	SIDL_C_INLINE_DECL_int32_t	

```
bHYPRE_StructMatrix_SetIntParameter ( bHYPRE_StructMatrix self,
                                            const char* name, int32_t value,
                                            sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructMatrix_SetDoubleParameter ( bHYPRE_StructMatrix
                                                self, const char* name,
                                                double value,
                                                sidl_BaseInterface *_ex)
      Set the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructMatrix_SetStringParameter ( bHYPRE_StructMatrix self,
                                               const char* name,
                                               const char* value,
                                               sidl_BaseInterface *_ex)
      Set the string parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructMatrix_SetIntArray1Parameter ( bHYPRE_StructMatrix
                                                   self, const char* name,
                                                   int32_t* value,
                                                   int32_t nvalues,
                                                   sidl_BaseInterface *_ex)
      Set the int 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructMatrix_SetIntArray2Parameter ( bHYPRE_StructMatrix
                                                   self, const char* name,
                                                   struct sidl_int_array*
                                                   value,
                                                   sidl_BaseInterface *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructMatrix_SetDoubleArray1Parameter (
                                                        bHYPRE_StructMatrix
                                                        self.
                                                        const char* name,
                                                        double* value,
                                                        int32_t nvalues.
                                                        sidl_BaseInterface
                                                        *_ex)
      Set the double 1-D array parameter associated with name
```

SIDL_C_INLINE_DECL int32_t

bHYPRE_StructMatrix_SetDoubleArray2Parameter (

```
bHYPRE_StructMatrix
                                                        self.
                                                        const char* name,
                                                        struct
                                                        sidl\_double\_array*
                                                        value.
                                                        sidl\_BaseInterface
                                                        *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructMatrix_GetIntValue ( bHYPRE_StructMatrix self,
                                        const char* name, int32_t* value,
                                        sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_StructMatrix_GetDoubleValue ( bHYPRE_StructMatrix self,
                                            const char* name,
                                            double* value,
                                            sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructMatrix_Setup ( bHYPRE_StructMatrix self,
                                 bHYPRE_Vector b, bHYPRE_Vector x,
                                sidl_BaseInterface *_ex)
       (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructMatrix_Apply ( bHYPRE_StructMatrix self,
                                 bHYPRE_Vector b, bHYPRE_Vector* x,
                                 sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL_int32_t
bHYPRE_StructMatrix_ApplyAdjoint ( bHYPRE_StructMatrix self,
                                         bHYPRE_Vector b,
                                         bHYPRE_Vector* x,
                                         sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_ex
       Cast method for interface and class type conversions
void*
bHYPRE_StructMatrix_cast2 (void* obj, const char* type,
                                 sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
```

bHYPRE_StructMatrix_exec (bHYPRE_StructMatrix self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex) Select and execute a method by name SIDL_C_INLINE_DECL char* bHYPRE_StructMatrix__getURL (bHYPRE_StructMatrix self, sidl_BaseInterface *_ex) Get the URL of the Implementation of this object (for RMI) SIDL_C_INLINE_DECL_void bHYPRE_StructMatrix_raddRef (bHYPRE_StructMatrix self, sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance SIDL_C_INLINE_DECL sidl_bool bHYPRE_StructMatrix_isRemote (bHYPRE_StructMatrix self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local sidl_bool bHYPRE_StructMatrix__isLocal (bHYPRE_StructMatrix self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local **_ex Cast method for interface and class type conversions $**_ex$ 4.3.13 RMI connector function for the class 68

4.3.1

struct bHYPRE_StructMatrix_object

Symbol "bHYPRE.StructMatrix" (version 1.0.0)

A single class that implements both a view interface and an operator interface. A StructMatrix is a matrix on a structured grid. One function unique to a StructMatrix is SetConstantEntries. This declares that matrix entries corresponding to certain stencil points (supplied as stencil element indices) will be constant throughout the grid.

 $_$ 4.3.2 $_$

bHYPRE_StructMatrix bHYPRE_StructMatrix_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

 $_{-}$ 4.3.3 $_{-}$

SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrix_SetGrid (bHYPRE_StructMatrix self, bHYPRE_StructGrid grid, sidl_BaseInterface *_ex)

Set the grid on which vectors are defined. This and the stencil determine the matrix structure.

 $_$ 4.3.4 $_$

SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrix_SetStencil (bHYPRE_StructMatrix self, bHYPRE_StructStencil stencil, sidl_BaseInterface *_ex)

Set the stencil. This and the grid determine the matrix structure.

4.3.5

int32_t

bHYPRE_StructMatrix_SetValues (bHYPRE_StructMatrix self, int32_t* index, int32_t dim, int32_t num_stencil_indices, int32_t* stencil_indices, double* values, sidl_BaseInterface *_ex)

Set matrix values at grid point, given by "index". You can supply values for one or more positions in the stencil. "index" is an array of size "dim"; and "stencil_indices" and "values" are arrays of size "num_stencil_indices".

4.3.6

 $int32_t$

bHYPRE_StructMatrix_SetBoxValues (bHYPRE_StructMatrix self, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t num_stencil_indices, int32_t* stencil_indices, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set matrix values throughout a box in the grid, specified by its lower and upper corners. You can supply these values for one or more positions in the stencil. Thus the total number of matrix values you supply, "nvalues", is num_stencil_indices x box_size, where box_size is the number of grid points in the box. The values array should be organized so all values for a given box point are together (i.e., the stencil index is the most rapidly varying). "ilower" and "iupper" are arrays of size "dim", "stencil_indices" is an array of size "num_stencil_indices", and "values" is an array of size "nvalues".

$_$ 4.3.7 $_$

SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrix_SetNumGhost (bHYPRE_StructMatrix self, int32_t* num_ghost, int32_t dim2, sidl_BaseInterface *_ex)

Set the number of ghost zones, separately on the lower and upper sides for each dimension. "num_ghost" is an array of size "dim2", twice the number of dimensions

_ 4.3.8 _

SIDL_C_INLINE_DECL int32_t **bHYPRE_StructMatrix_SetConstantEntries** (bHYPRE_StructMatrix self, int32_t num_stencil_constant_points, int32_t* stencil_constant_points, sidl_BaseInterface *_ex)

State which stencil entries are constant over the grid. Supported options are: (i) none (the default), (ii) all (stencil_constant_points should include all stencil points) (iii) all entries but the diagonal.

4.3.9

 $int32_t$

bHYPRE_StructMatrix_SetConstantValues (bHYPRE_StructMatrix self, int32_t num_stencil_indices, int32_t* stencil_indices, double* values, sidl_BaseInterface *_ex)

Provide values for matrix coefficients which are constant throughout the grid, one value for each stencil point. "stencil_indices" and "values" is each an array of length "num_stencil_indices"

4.3.10

SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrix_SetCommunicator (bHYPRE_StructMatrix self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, Use Create()

4.3.11

SIDL_C_INLINE_DECL void **bHYPRE_StructMatrix_Destroy** (bHYPRE_StructMatrix self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

 $_$ 4.3.12 $_$

SIDL_C_INLINE_DECL int32_t bHYPRE_StructMatrix_Assemble (bHYPRE_StructMatrix self, sidl_BaseInterface *_ex)

Finalize the construction of an object before using, either for the first time or on subsequent uses. Initialize and Assemble always appear in a matched set, with Initialize preceding Assemble. Values can only be set in between a call to Initialize and Assemble.

4.3.13

RMI connector function for the class. (no addref)

_ 4.4 _

Struct Vector

Names		
4.4.1	struct bHYPRE_StructVector_object Symbol "bHYPRE	71
	_ex	
	Constructor function for the class	
	bHYPRE_StructVector bHYPRE_StructVectorcreateRemote (const char * url, sidl_BaseInterface *_ex)	
	RMI constructor function for the class	
	bHYPRE_StructVector bHYPRE_StructVectorwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_StructVectordata) passed in rather than running the con- structor	
4.4.2	bHYPRE_StructVector bHYPRE_StructVectorconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	71
	bHYPRE_StructVector bHYPRE_MPICommunicator mpi_comm, bHYPRE_StructGrid grid, sidl_BaseInterface *_ex) This function is the preferred way to create a Struct Vector	
	SIDL_C_INLINE_DECL int32_t bHYPRE_StructVector_SetGrid (bHYPRE_StructVector self,	
4.4.3	SIDL C INLINE DECL, int32 t	

	bHYPRE_StructVector_SetNumGhost (bHYPRE_StructVector self, int32_t* num_ghost, int32_t dim2, sidl_BaseInterface *_ex)
	Set the number of ghost zones, separately on the lower and upper sides for each dimension
4.4.4	SIDL_C_INLINE_DECL int32_t bHYPRE_StructVector_SetValue (bHYPRE_StructVector self,
	double value, sidl_BaseInterface *_ex) Set the value of a single vector coefficient, given by "grid_index"
4.4.5	int32_t bHYPRE_StructVector_SetBoxValues (bHYPRE_StructVector self,
	sidl_BaseInterface *_ex) Set the values of all vector coefficient for grid points in a box
4.4.6	SIDL_C_INLINE_DECL_int32_t bHYPRE_StructVector_SetCommunicator (bHYPRE_StructVector self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)
	Set the MPI Communicator
4.4.7	SIDL_C_INLINE_DECL_void bHYPRE_StructVector_Destroy (bHYPRE_StructVector self,
	SIDL_C_INLINE_DECL int32_t bHYPRE_StructVector_Initialize (bHYPRE_StructVector self,
	subsequently
4.4.8	SIDL_C_INLINE_DECL int32_t bHYPRE_StructVector_Assemble (bHYPRE_StructVector self, sidl_BaseInterface *_ex)
	Finalize the construction of an object before using, either for the first time or on subsequent uses
	SIDL_C_INLINE_DECL int32_t bHYPRE_StructVector_Clear (bHYPRE_StructVector self,
	Set self to θ
	SIDL_C_INLINE_DECL_int32_t bHYPRE_StructVector_Copy (bHYPRE_StructVector self,
	$Copy \ data \ from \ x \ into \ {\tt self}$
4.4.9	SIDL_C_INLINE_DECL int32_t bHYPRE_StructVector_Clone (bHYPRE_StructVector self,
	Create an x compatible with self
	SIDL_C_INLINE_DECL int32_t

bHYPRE_StructVector_Scale (bHYPRE_StructVector self, double a,

```
sidl_BaseInterface *_ex)
      Scale  self by a
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructVector_Dot ( bHYPRE_StructVector self,
                              bHYPRE_Vector x, double* d,
                              sidl_BaseInterface *_ex)
      Compute d, the inner-product of self and x
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructVector_Axpy ( bHYPRE_StructVector self, double a,
                                bHYPRE_Vector x, sidl_BaseInterface *_ex)
      Add ax to self
_ex
      Cast method for interface and class type conversions
void*
bHYPRE_StructVector__cast2 (void* obj, const char* type,
                                sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
bHYPRE_StructVector_exec ( bHYPRE_StructVector self,
                               const char* methodName,
                               sidl_rmi_Call inArgs, sidl_rmi_Return outArgs,
                               sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL char*
bHYPRE_StructVector__getURL ( bHYPRE_StructVector self,
                                   sidl_BaseInterface *_ex)
      Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL void
bHYPRE_StructVector_raddRef ( bHYPRE_StructVector self,
                                   sidl_BaseInterface *_ex)
      On a remote object, addrefs the remote instance
SIDL_C_INLINE_DECL sidl_bool
bHYPRE_StructVector_isRemote ( bHYPRE_StructVector self,
                                    sidl_BaseInterface *_ex)
       TRUE if this object is remote, false if local
sidl_bool
bHYPRE_StructVector_isLocal ( bHYPRE_StructVector self,
                                  sidl_BaseInterface *_ex)
      TRUE if this object is remote, false if local
**_ex
      Cast method for interface and class type conversions
**_ex
      RMI connector function for the class ......
                                                                                 73
```

4.4.10

_ 4.4.1 _____

struct bHYPRE_StructVector_object

Symbol "bHYPRE.StructVector" (version 1.0.0)

4.4.2

bHYPRE_StructVector bHYPRE_StructVector__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

_ 4.4.3 ____

SIDL_C_INLINE_DECL int32_t bHYPRE_StructVector_SetNumGhost (bHYPRE_StructVector self, int32_t* num_ghost, int32_t dim2, sidl_BaseInterface *_ex)

Set the number of ghost zones, separately on the lower and upper sides for each dimension. "num_ghost" is an array of size "dim2", twice the number of dimensions.

_ 4.4.4 _

SIDL_C_INLINE_DECL int32_t bHYPRE_StructVector_SetValue (bHYPRE_StructVector self, int32_t* grid_index, int32_t dim, double value, sidl_BaseInterface *_ex)

Set the value of a single vector coefficient, given by "grid_index". "grid_index" is an array of size "dim", where dim is the number of dimensions.

4.4.5

 $int32_t$

bHYPRE_StructVector_SetBoxValues (bHYPRE_StructVector self, int32_t* ilower, int32_t* iupper, int32_t dim, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set the values of all vector coefficient for grid points in a box. The box is defined by its lower and upper corners in the grid. "ilower" and "iupper" are arrays of size "dim", where dim is the number of dimensions. The "values" array has size "nvalues", which is the number of grid points in the box.

__ 4.4.6 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_StructVector_SetCommunicator (bHYPRE_StructVector self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, Use Create()

4.4.7

SIDL_C_INLINE_DECL void bHYPRE_StructVector_Destroy (bHYPRE_StructVector self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

4.4.8

SIDL_C_INLINE_DECL int32_t bHYPRE_StructVector_Assemble (bHYPRE_StructVector self, sidl_BaseInterface *_ex)

Finalize the construction of an object before using, either for the first time or on subsequent uses. Initialize and Assemble always appear in a matched set, with Initialize preceding Assemble. Values can only be set in between a call to Initialize and Assemble.

4.4.9

SIDL_C_INLINE_DECL int32_t bHYPRE_StructVector_Clone (bHYPRE_StructVector self, bHYPRE_Vector* x, sidl_BaseInterface *_ex)

Create an x compatible with self. The new vector's data is not specified.

NOTE: When this method is used in an inherited class, the cloned Vector object can be cast to an object with the inherited class type.

_ 4.4.10 _

struct bHYPRE_StructVector_object* bHYPRE_StructVector_connectI const char * url sidl_bool ar struct sidl_BaseInterface_object **-ex

RMI connector function for the class. (no addref)

_ 4.5 _

SemiStructured Matrix

Names

78

_ex

Constructor function for the class

 $bHYPRE_SStructMatrix$

 $\mathbf{bHYPRE_SStructMatrix__createRemote} \ (\mathrm{const} \ \mathrm{char} \ ^* \ \mathrm{url},$

sidl_BaseInterface *_ex)

RMI constructor function for the class

bHYPRE_SStructMatrix

	bHYPRE_SStructMatrixwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_SStructMatrixdata) passed in rather than running the con- structor	
4.5.2	bHYPRE_SStructMatrix bHYPRE_SStructMatrixconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	79
	bHYPRE_SStructMatrix_Create (bHYPRE_MPICommunicator mpi_comm, bHYPRE_SStructGraph graph, sidl_BaseInterface *_ex)	
	This function is the preferred way to create a SStruct Matrix	
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_SetObjectType (bHYPRE_SStructMatrix self, int32_t type, sidl_BaseInterface *_ex)	
	$Method:\ SetObjectType[]$	
4.5.3	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_SetGraph (bHYPRE_SStructMatrix self, bHYPRE_SStructGraph graph, sidl_BaseInterface *_ex)	
	Set the matrix graph	79
4.5.4	int32_t bHYPRE_SStructMatrix_SetValues (bHYPRE_SStructMatrix self,	79
4.5.5	int32_t bHYPRE_SStructMatrix_SetBoxValues (bHYPRE_SStructMatrix self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, int32_t nvalues, sidl_BaseInterface *_ex) Set matrix coefficients a box at a time	80
4.5.6	int32_t bHYPRE_SStructMatrix_AddToValues (bHYPRE_SStructMatrix self, int32_t part, int32_t* index, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, sidl_BaseInterface *_ex) Add to matrix coefficients index by index	80
4.5.7	$\mathrm{int}32_{-}\mathrm{t}$	

	bHYPRE_SStructMatrix_AddToBoxValues (bHYPRE_SStructMatrix self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, int32_t nvalues, sidl_BaseInterface *_ex) Add to matrix coefficients a box at a time	81
1 5 0		01
4.5.8	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_SetSymmetric (bHYPRE_SStructMatrix self,	
	Define symmetry properties for the stencil entries in the matrix	81
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_SetNSSymmetric (bHYPRE_SStructMatrix self, int32_t symmetric, sidl_BaseInterface *_ex) Define symmetry properties for all non-stencil matrix entries	
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_SetComplex (bHYPRE_SStructMatrix self, sidl_BaseInterface *_ex)	
	Set the matrix to be complex	
4.5.9	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_Print (bHYPRE_SStructMatrix self,	
	Print the matrix to file	81
4.5.10	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_GetObject (bHYPRE_SStructMatrix self, sidl_BaseInterface* A, sidl_BaseInterface *_ex) A semi-structured matrix or vector contains a Struct or IJ matrix or vector	
		82
4.5.11	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_SetCommunicator (bHYPRE_SStructMatrix self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)	
	Set the MPI Communicator	82
4.5.12	SIDL_C_INLINE_DECL void bHYPRE_SStructMatrix_Destroy (bHYPRE_SStructMatrix self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	82
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_SStructMatrix_Initialize ( bHYPRE_SStructMatrix self,
                                                 sidl_BaseInterface *_ex)
                   Prepare an object for setting coefficient values, whether for the first time or
                   subsequently
4.5.13
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_SStructMatrix_Assemble ( bHYPRE_SStructMatrix self,
                                                 sidl_BaseInterface *_ex)
                   Finalize the construction of an object before using, either for the first time
                   or on subsequent uses .....
                                                                                             83
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_SStructMatrix_SetIntParameter ( bHYPRE_SStructMatrix self,
                                                         const char* name,
                                                         int32_t value,
                                                         sidl_BaseInterface *_ex)
                   Set the int parameter associated with name
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_SStructMatrix_SetDoubleParameter ( bHYPRE_SStructMatrix
                                                             self, const char* name,
                                                             double value,
                                                             sidl_BaseInterface *_ex)
                   Set the double parameter associated with name
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_SStructMatrix_SetStringParameter ( bHYPRE_SStructMatrix
                                                            self, const char* name,
                                                            const char* value.
                                                            sidl\_BaseInterface *\_ex)
                   Set the string parameter associated with name
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_SStructMatrix_SetIntArray1Parameter (
                                                                bHYPRE_SStructMatrix
                                                                self, const char* name,
                                                                int32_t* value,
                                                                int32_t nvalues.
                                                                sidl_BaseInterface *_ex)
                   Set the int 1-D array parameter associated with name
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_SStructMatrix_SetIntArray2Parameter (
                                                                bHYPRE SStructMatrix
                                                                self, const char* name,
                                                                struct sidl_int_array*
                                                                sidl_BaseInterface *_ex)
                   Set the int 2-D array parameter associated with name
```

SIDL_C_INLINE_DECL int32_t

```
bHYPRE_SStructMatrix_SetDoubleArray1Parameter (
                                                        bHYPRE_SStructMatrix
                                                        const char* name,
                                                        double* value,
                                                        int32_t nvalues,
                                                        sidl_BaseInterface
                                                         *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructMatrix_SetDoubleArray2Parameter (
                                                        bHYPRE_SStructMatrix
                                                        self,
                                                        const char* name.
                                                        struct
                                                        sidl_double_array*
                                                        value,
                                                        sidl_BaseInterface
                                                        *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructMatrix_GetIntValue ( bHYPRE_SStructMatrix self,
                                        const char* name, int32_t* value,
                                        sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructMatrix_GetDoubleValue ( bHYPRE_SStructMatrix self,
                                             const char* name.
                                             double* value,
                                             sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructMatrix_Setup ( bHYPRE_SStructMatrix self,
                                  bHYPRE_Vector b, bHYPRE_Vector x,
                                 sidl_BaseInterface *_ex)
      (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructMatrix_Apply ( bHYPRE_SStructMatrix self,
                                  bHYPRE_Vector b, bHYPRE_Vector* x,
                                  sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructMatrix_ApplyAdjoint ( bHYPRE_SStructMatrix self,
                                          bHYPRE_Vector b,
                                          bHYPRE_Vector* x,
                                          sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_ex
```

Cast method for interface and class type conversions

void*

bHYPRE_SStructMatrix__cast2 (void* obj, const char* type, sidl_BaseInterface *_ex)

String cast method for interface and class type conversions

SIDL_C_INLINE_DECL void

bHYPRE_SStructMatrix__exec (bHYPRE_SStructMatrix self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex)

Select and execute a method by name

SIDL_C_INLINE_DECL char*

bHYPRE_SStructMatrix__getURL (bHYPRE_SStructMatrix self, sidl_BaseInterface *_ex)

Get the URL of the Implementation of this object (for RMI)

SIDL_C_INLINE_DECL void

bHYPRE_SStructMatrix_raddRef (bHYPRE_SStructMatrix self, sidl_BaseInterface *_ex)

On a remote object, addrefs the remote instance

SIDL_C_INLINE_DECL sidl_bool

bHYPRE_SStructMatrix__isRemote (bHYPRE_SStructMatrix self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

sidl_bool

 $\begin{tabular}{ll} \bf bHYPRE_SStructMatrix_isLocal (bHYPRE_SStructMatrix self, \\ sidl_BaseInterface *_ex) \end{tabular}$

TRUE if this object is remote, false if local

**_ex

Cast method for interface and class type conversions

4.5.14 **_ex

RMI connector function for the class

4.5.1

struct bHYPRE_SStructMatrix_object

Symbol "bHYPRE.SStructMatrix" (version 1.0.0)

The semi-structured grid matrix class.

Objects of this type can be cast to SStructMatrixView or Operator objects using the __cast methods.

83

4.5.2

bHYPRE_SStructMatrix bHYPRE_SStructMatrix_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

 $_$ 4.5.3 $_$

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_SetGraph (bHYPRE_SStructMatrix self, bHYPRE_SStructGraph graph, sidl_BaseInterface *_ex)

Set the matrix graph. DEPRECATED Use Create

4.5.4

 $int32_t$

bHYPRE_SStructMatrix_SetValues (bHYPRE_SStructMatrix self, int32_t part, int32_t* index, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, sidl_BaseInterface *_ex)

Set matrix coefficients index by index.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type (there are no such restrictions for non-stencil entries).

If the matrix is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

4.5.5

$int32_t$

bHYPRE_SStructMatrix_SetBoxValues (bHYPRE_SStructMatrix self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set matrix coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type (there are no such restrictions for non-stencil entries).

If the matrix is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

4.5.6

$int32_t$

bHYPRE_SStructMatrix_AddToValues (bHYPRE_SStructMatrix self, int32_t part, int32_t* index, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, sidl_BaseInterface *_ex)

Add to matrix coefficients index by index.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type.

If the matrix is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

$_{-}$ 4.5.7 $_{-}$

bHYPRE_SStructMatrix_AddToBoxValues (bHYPRE_SStructMatrix self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Add to matrix coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of stencil type. Also, they must all represent couplings to the same variable type.

If the matrix is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

4.5.8

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_SetSymmetric (bHYPRE_SStructMatrix self, int32_t part, int32_t var, int32_t to_var, int32_t symmetric, sidl_BaseInterface *_ex)

Define symmetry properties for the stencil entries in the matrix. The boolean argument symmetric is applied to stencil entries on part part that couple variable var to variable to_var. A value of -1 may be used for part, var, or to_var to specify "all". For example, if part and to_var are set to -1, then the boolean is applied to stencil entries on all parts that couple variable var to all other variables.

By default, matrices are assumed to be nonsymmetric. Significant storage savings can be made if the matrix is symmetric.

4.5.9

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_Print (bHYPRE_SStructMatrix self, const char* filename, int32_t all, sidl_BaseInterface *_ex)

Print the matrix to file. This is mainly for debugging purposes.

4.5.10

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_GetObject (bHYPRE_SStructMatrix self, sidl_BaseInterface* A, sidl_BaseInterface*_ex)

A semi-structured matrix or vector contains a Struct or IJ matrix or vector. GetObject returns it. The returned type is a sidl.BaseInterface. A cast must be used on the returned object to convert it into a known type.

4.5.11

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_SetCommunicator (bHYPRE_SStructMatrix self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, Use Create()

4.5.12 $_$

SIDL_C_INLINE_DECL void **bHYPRE_SStructMatrix_Destroy** (bHYPRE_SStructMatrix self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

4.5.13

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructMatrix_Assemble (bHYPRE_SStructMatrix self, sidl_BaseInterface *_ex)

Finalize the construction of an object before using, either for the first time or on subsequent uses. Initialize and Assemble always appear in a matched set, with Initialize preceding Assemble. Values can only be set in between a call to Initialize and Assemble.

4.5.14

RMI connector function for the class. (no addref)

4.6

SemiStructured Vector

Names

4.6.1 struct bHYPRE_SStructVector_object Symbol "bHYPRE 87 _ex Constructor function for the class bHYPRE_SStructVector bHYPRE_SStructVector__createRemote (const char * url, sidl_BaseInterface *_ex) RMI constructor function for the class bHYPRE_SStructVector bHYPRE_SStructVector__wrapObj (void * data, sidl_BaseInterface *_ex) theprivatedatastructbHYPRE_SStructVector_data) passed in rather than running the constructor4.6.2 bHYPRE_SStructVector bHYPRE_SStructVector__connect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class 87 $bHYPRE_SStructVector$

	bHYPRE_SStructVector_Create (bHYPRE_MPICommunicator mpi_comm, bHYPRE_SStructGrid grid,	
	sidl_BaseInterface *_ex)	
	This function is the preferred way to create a SStruct Vector	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructVector_SetObjectType (bHYPRE_SStructVector self,	
	$int32_{-}t type, \\ sidl_BaseInterface *_ex)$	
	Method: SetObjectType[]	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructVector_SetGrid (bHYPRE_SStructVector self,	
	bHYPRE_SStructGrid grid,	
	sidl_BaseInterface *_ex)	
	Set the vector grid	
1.6.3	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructVector_SetValues (bHYPRE_SStructVector self, int32_t part, int32_t* index,	
	int32_t dim, int32_t var, double value,	
	sidl_BaseInterface *_ex)	
	Set vector coefficients index by index	87
1.6.4	$\mathrm{int}32_\mathrm{t}$	
	bHYPRE_SStructVector_SetBoxValues (bHYPRE_SStructVector self,	
	int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim,	
	int32_t var, double* values,	
	int32t nvalues,	
	sidl_BaseInterface *_ex)	0.0
	Set vector coefficients a box at a time	88
1.6.5	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVector_AddToValues (bHYPRE_SStructVector self,	
	int32_t part, int32_t* index,	
	$int32_t dim, int32_t var,$	
	double value,	
	sidl_BaseInterface *_ex) Set vector coefficients index by index	88
100	200 00000 000000 000000 000000 00000000	00
1.6.6	int32_t bHYPRE_SStructVector_AddToBoxValues (bHYPRE_SStructVector self,	
	int32_t part, int32_t* ilower,	
	$int32_t^* iupper$, $int32_t dim$,	
	int32_t var, double* values,	
	int32_t nvalues, sidl_BaseInterface *_ex)	
	Set vector coefficients a box at a time	89
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructVector_Gather (bHYPRE_SStructVector self, sidl_BaseInterface *_ex)	
	Gather vector data before calling GetValues	
1.6.7	SIDL_C_INLINE_DECL_int32_t	

	bHYPRE_SStructVector_GetValues (bHYPRE_SStructVector self, int32_t part, int32_t* index, int32_t dim, int32_t var, double* value, sidl_BaseInterface *_ex)	
	Get vector coefficients index by index	89
4.6.8	int32_t bHYPRE_SStructVector_GetBoxValues (bHYPRE_SStructVector self,	
	int32_t part, int32_t nower, int32_t* iupper, int32_t dim, int32_t var, double* values, int32_t nvalues, sidl_BaseInterface *_ex)	
	Get vector coefficients a box at a time	89
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVector_SetComplex (bHYPRE_SStructVector self, sidl_BaseInterface *_ex)	
	Set the vector to be complex	
4.6.9	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVector_Print (bHYPRE_SStructVector self,	
	sidl_BaseInterface *_ex) Print the vector to file	90
4.6.10	bHYPRE_SStructVector_GetObject (bHYPRE_SStructVector self, sidl_BaseInterface* A,	
	sidl_BaseInterface *_ex) A semi-structured matrix or vector contains a Struct or IJ matrix or vector	0.0
		90
4.6.11	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVector_SetCommunicator (bHYPRE_SStructVector self, bHYPRE_MPICommunicator	
	mpi_comm, sidl_BaseInterface *_ex)	
	Set the MPI Communicator	90
4.6.12	SIDL_C_INLINE_DECL_void	
	bHYPRE_SStructVector_Destroy (bHYPRE_SStructVector self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	90
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVector_Initialize (bHYPRE_SStructVector self,	
	Prepare an object for setting coefficient values, whether for the first time or subsequently	
4.6.13	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVector_Assemble (bHYPRE_SStructVector self, sidl_BaseInterface *_ex)	
	Finalize the construction of an object before using, either for the first time or on subsequent uses	91
	SIDL C INLINE DECL. int32 t	

```
bHYPRE_SStructVector_Clear ( bHYPRE_SStructVector self,
                                               sidl_BaseInterface *_ex)
                    Set \ {\tt self} \ to \ \theta
             SIDL_C_INLINE_DECL int32_t
             bHYPRE_SStructVector_Copy ( bHYPRE_SStructVector self,
                                               bHYPRE_Vector x, sidl_BaseInterface *_ex)
                    Copy data from x into self
             SIDL_C_INLINE_DECL int32_t
4.6.14
             bHYPRE_SStructVector_Clone ( bHYPRE_SStructVector self,
                                               bHYPRE_Vector* x,
                                               sidl_BaseInterface *_ex)
                    Create an x compatible with self .....
                                                                                                 91
             SIDL_C_INLINE_DECL int32_t
             bHYPRE_SStructVector_Scale ( bHYPRE_SStructVector self, double a,
                                               sidl_BaseInterface *_ex)
                    Scale \ \mathtt{self} \ by \ \mathtt{a}
             SIDL_C_INLINE_DECL int32_t
             bHYPRE_SStructVector_Dot ( bHYPRE_SStructVector self,
                                             bHYPRE_Vector x, double* d,
                                             sidl_BaseInterface *_ex)
                    Compute d, the inner-product of self and x
             SIDL_C_INLINE_DECL_int32_t
             bHYPRE_SStructVector_Axpy ( bHYPRE_SStructVector self, double a,
                                               bHYPRE_Vector x, sidl_BaseInterface *_ex)
                    Add ax to self
             _ex
                    Cast method for interface and class type conversions
             void*
             bHYPRE_SStructVector__cast2 (void* obj, const char* type,
                                               sidl_BaseInterface *_ex)
                    String cast method for interface and class type conversions
             SIDL_C_INLINE_DECL void
             bHYPRE_SStructVector_exec ( bHYPRE_SStructVector self,
                                               const char* methodName,
                                               sidl_rmi_Call inArgs,
                                               sidl_rmi_Return outArgs,
                                               sidl_BaseInterface *_ex)
                    Select and execute a method by name
             SIDL_C_INLINE_DECL_char*
             bHYPRE_SStructVector__getURL ( bHYPRE_SStructVector self,
                                                   sidl_BaseInterface *_ex)
                    Get the URL of the Implementation of this object (for RMI)
             SIDL_C_INLINE_DECL void
             \mathbf{bHYPRE\_SStructVector\_raddRef} \ ( \ \ \mathbf{bHYPRE\_SStructVector} \ \mathbf{self},
                                                   sidl_BaseInterface *_ex)
                    On a remote object, addrefs the remote instance
             SIDL_C_INLINE_DECL_sidl_bool
```

bHYPRE_SStructVector__isRemote (bHYPRE_SStructVector self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

sidl_bool

bHYPRE_SStructVector__isLocal (bHYPRE_SStructVector self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

 $**_{-}ex$

Cast method for interface and class type conversions

4.6.15 **_ex

RMI connector function for the class

4.6.1

struct bHYPRE_SStructVector_object

Symbol "bHYPRE.SStructVector" (version 1.0.0)

The semi-structured grid vector class.

Objects of this type can be cast to SStructVectorView or Vector objects using the __cast methods.

_ 4.6.2 __

 $b HYPRE_SStructVector$

bHYPRE_SStructVector_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

4.6.3

SIDL_C_INLINE_DECL int32_t

bHYPRE_SStructVector_SetValues (bHYPRE_SStructVector self, int32_t part, int32_t* index, int32_t dim, int32_t var, double value, sidl_BaseInterface *_ex)

91

Set vector coefficients index by index.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

If the vector is complex, then value consists of a pair of doubles representing the real and imaginary parts of the complex value.

4.6.4

int32_t

bHYPRE_SStructVector_SetBoxValues (bHYPRE_SStructVector self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set vector coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

If the vector is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

4.6.5

SIDL_C_INLINE_DECL int32_t

bHYPRE_SStructVector_AddToValues (bHYPRE_SStructVector self, int32_t part, int32_t* index, int32_t dim, int32_t var, double value, sidl_BaseInterface *_ex)

Set vector coefficients index by index.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

If the vector is complex, then value consists of a pair of doubles representing the real and imaginary parts of the complex value.

4.6.6

$int32_t$

bHYPRE_SStructVector_AddToBoxValues (bHYPRE_SStructVector self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set vector coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

If the vector is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

4.6.7

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVector_GetValues (bHYPRE_SStructVector self, int32_t part, int32_t* index, int32_t dim, int32_t var, double* value, sidl_BaseInterface *_ex)

Get vector coefficients index by index.

NOTE: Users may only get values on processes that own the associated variables.

If the vector is complex, then value consists of a pair of doubles representing the real and imaginary parts of the complex value.

4.6.8

$int32_t$

bHYPRE_SStructVector_GetBoxValues (bHYPRE_SStructVector self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Get vector coefficients a box at a time.

NOTE: Users may only get values on processes that own the associated variables.

If the vector is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

__ 4.6.9 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVector_Print (bHYPRE_SStructVector self, const char* filename, int32_t all, sidl_BaseInterface *_ex)

Print the vector to file. This is mainly for debugging purposes.

__ 4.6.10 ___

SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructVector_GetObject (bHYPRE_SStructVector self,
sidl_BaseInterface* A, sidl_BaseInterface*_ex)

A semi-structured matrix or vector contains a Struct or IJ matrix or vector. GetObject returns it. The returned type is a sidl.BaseInterface. A cast must be used on the returned object to convert it into a known type.

4.6.11

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVector_SetCommunicator (bHYPRE_SStructVector self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, Use Create()

 $_ \ \ 4.6.12 \ \ ___$

SIDL_C_INLINE_DECL void **bHYPRE_SStructVector_Destroy** (bHYPRE_SStructVector self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

4.6.13

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVector_Assemble (bHYPRE_SStructVector self, sidl_BaseInterface *_ex)

Finalize the construction of an object before using, either for the first time or on subsequent uses. Initialize and Assemble always appear in a matched set, with Initialize preceding Assemble. Values can only be set in between a call to Initialize and Assemble.

_ 4.6.14 __

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructVector_Clone (bHYPRE_SStructVector self, bHYPRE_Vector* x, sidl_BaseInterface *_ex)

Create an x compatible with self. The new vector's data is not specified.

NOTE: When this method is used in an inherited class, the cloned Vector object can be cast to an object with the inherited class type.

4.6.15

RMI connector function for the class. (no addref)

_ 4.7 _

SemiStructured ParCSR Matrix

Names		
4.7.1	struct bHYPRE_SStructParCSRMatrix_object Symbol "bHYPRE	98
	_ex	
	Constructor function for the class	
	bHYPRE_SStructParCSRMatrix bHYPRE_SStructParCSRMatrixcreateRemote (const char * url, sidl_BaseInterface *_ex)	
	RMI constructor function for the class	
	bHYPRE_SStructParCSRMatrix bHYPRE_SStructParCSRMatrixwrapObj (void * data, sidl_BaseInterface *_ex)	
	$Wraps$ up the private data struct pointer (struct $bHYPRE_SStructParCSRMatrix_data$) passed in rather than running the constructor	
4.7.2	bHYPRE_SStructParCSRMatrix bHYPRE_SStructParCSRMatrixconnect (const char *,	
	RMI connector function for the class	98
	bHYPRE_SStructParCSRMatrix_Create (bHYPRE_MPICommunicator mpi_comm, bHYPRE_SStructGraph graph, sidl_BaseInterface *_ex) This function is the preferred way to create a SStruct ParCSR Matrix	
4.7.3	SIDL_C_INLINE_DECL int32_t	
1.1.0	bHYPRE_SStructParCSRMatrix_SetGraph (
	bHYPRE_SStructParCSRMatrix self, bHYPRE_SStructGraph graph, sidl_BaseInterface *_ex)	00
	Set the matrix graph	99
4.7.4	$int 32_t$ bHYPRE_SStructParCSRMatrix_SetValues (
	bHYPRE_SStructParCSRMatrix self, int32_t part, int32_t* index, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, sidl_BaseInterface *_ex)	
	Set matrix coefficients index by index	99
4.7.5	$\mathrm{int}32_\mathrm{t}$	

	bHYPRE_SStructParCSRMatrix_SetBoxVa	dues (
		bHYPRE_SStructParCSRMatrix
		self, int32_t part,
		int32_t* ilower,
		int32_t* iupper,
		int32_t dim, int32_t var,
		int32_t nentries,
		int32_t* entries,
		double* values,
		•
		int32_t nvalues,
		sidl_BaseInterface *_ex)
	Set matrix coefficients a box at a time	99
4.7.6	$\mathrm{int}32_\mathrm{t}$	
	$b HYPRE_SStructParCSRMatrix_AddToVa$	lues (
		$bHYPRE_SStructParCSRMatrix$
		self, int32_t part,
		$int32_t^* index,$
		int32_t dim, int32_t var,
		int32 _{-t} nentries,
		int32_t* entries,
		double* values,
		sidl_BaseInterface *_ex)
	Add to matrix coefficients index by index	
	· · ·	100
1.7.7	int32_t	
	$b HYPRE_SStructParCSRMatrix_AddToBo$	
		bHYPRE_SStructParCSRMatrix
		self, int32_t part,
		$int32_{-}t^{*}$ ilower,
		$int32_{-}t^*$ iupper,
		$int32_{-}t dim,$
		$int32_{-}t var,$
		int32_t nentries,
		int32_t* entries,
		double* values,
		int32_t nvalues,
		sidl_BaseInterface
		*_ex)
	Add to matrix coefficients a box at a time	
	**	
1.7.8	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructParCSRMatrix_SetSymm	`
		bHYPRE_SStructParCSRMatrix
		$self$, $int32_t part$,
		$int32_{-}t var,$
		int32_t to_var,
		int32_t symmetric,
		$sidl_BaseInterface *_ex)$
	Define symmetry properties for the stencil	entries in the matrix 101
	SIDL_C_INLINE_DECL int32_t	
	DIDIDOLINI DI	

	bHYPRE_SStructParCSRMatrix_SetNSSymmetric (
	bHYPRE_SStructParCSRMatr	ix
	$\operatorname{self},$	
	int32_t symmetric,	
	$sidl_BaseInterface$ *_ex)	
	Define symmetry properties for all non-stencil matrix entries	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructParCSRMatrix_SetComplex (
	bHYPRE_SStructParCSRMatrix	
	$\operatorname{self},$	
	sidl_BaseInterface *_ex)	
4 = 0	Set the matrix to be complex	
4.7.9	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRMatrix_Print (bHYPRE_SStructParCSRMatrix	
	self, const char* filename,	
	int32_t all, sidl_BaseInterface *_ex)	
	Print the matrix to file	01
4.7.10	SIDL_C_INLINE_DECL int32_t	
	${\bf bHYPRE_SStructParCSRMatrix_GetObject} \ ($	
	bHYPRE_SStructParCSRMatrix	
	self, sidl_BaseInterface* A, sidl_BaseInterface *_ex)	
	A semi-structured matrix or vector contains a Struct or IJ matrix or vector	
		01
4.7.11	SIDL_C_INLINE_DECL_int32_t	
	${\bf bHYPRE_SStructParCSRMatrix_SetCommunicator}\ ($	
	bHYPRE_SStructParCSRMat	rix
	$\begin{array}{c} \text{self,} \\ \text{bHYPRE_MPICommunicator} \end{array}$	
	mpi_comm,	
	sidl_BaseInterface	
	*_ex)	
	Set the MPI Communicator	02
4.7.12	SIDL_C_INLINE_DECL void	
	bHYPRE_SStructParCSRMatrix_Destroy (
	bHYPRE_SStructParCSRMatrix	
	self, sidl_BaseInterface *_ex) The Destroy function doesn't necessarily destroy anything	02
	SIDL_C_INLINE_DECL int32_t	_
	bHYPRE_SStructParCSRMatrix_Initialize (
	bHYPRE_SStructParCSRMatrix	
	self, sidl_BaseInterface *_ex)	
	Prepare an object for setting coefficient values, whether for the first time or subsequently	
4.7.13	SIDL_C_INLINE_DECL_int32_t	

```
bHYPRE_SStructParCSRMatrix_Assemble (
                                             bHYPRE_SStructParCSRMatrix
                                             self, sidl_BaseInterface *_ex)
      Finalize the construction of an object before using, either for the first time
      or on subsequent uses .....
                                                                               102
SIDL_C_INLINE_DECL int32_t
{\bf bHYPRE\_SStructParCSRMatrix\_SetIntParameter}\ (
                                                    bHYPRE_SStructParCSRMatrix
                                                    self.
                                                    const char* name,
                                                    int32_t value,
                                                    sidl_BaseInterface
                                                    *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_SStructParCSRMatrix_SetDoubleParameter (
                                                        bHYPRE_SStructParCSRMatrix
                                                        self.
                                                        const char* name,
                                                        double value.
                                                        sidl_BaseInterface
                                                        *_ex)
      Set the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE\_SStructParCSRMatrix\_SetStringParameter \ (
                                                       bHYPRE_SStructParCSRMatrix
                                                       self,
                                                       const char* name.
                                                       const char* value,
                                                       sidl_BaseInterface
                                                       *_ex)
      Set the string parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructParCSRMatrix_SetIntArray1Parameter (
                                                           bHYPRE_SStructParCSRMatrix
                                                           self, const
                                                           char* name,
                                                           int32_t* value,
                                                           int 32\_t
                                                           nvalues,
                                                           sidl_BaseInterface
                                                           *_ex)
      Set the int 1-D array parameter associated with name
```

SIDL_C_INLINE_DECL int32_t

```
bHYPRE_SStructParCSRMatrix_SetIntArray2Parameter (
                                                              bHYPRE_SStructParCSRMatrix
                                                              self, const
                                                              char* name,
                                                              struct
                                                              sidl_int_array*
                                                              value.
                                                              sidl\_BaseInterface
                                                              *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
{\bf bHYPRE\_SStructParCSRMatrix\_SetDoubleArray1Parameter}\ (
                                                                  bHYPRE_SStructParCSRMatrix
                                                                  self.
                                                                  const
                                                                  char*
                                                                  name,
                                                                  double*
                                                                  value,
                                                                  int32_t
                                                                  nvalues.
                                                                  sidl_BaseInterface
                                                                  *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
b HYPRE\_SStructParCSRMatrix\_SetDoubleArray2Parameter\ (
                                                                  bHYPRE_SStructParCSRMatrix
                                                                  self.
                                                                  const
                                                                  char^*
                                                                  name,
                                                                  struct
                                                                  sidl_double_array*
                                                                  value,
                                                                  sidl_BaseInterface
                                                                  *_ex)
      Set the double 2-D array parameter associated with name
SIDL\_C\_INLINE\_DECL\ int 32\_t
bHYPRE_SStructParCSRMatrix_GetIntValue (
                                                  b HYPRE\_SStructParCSRMatrix
                                                  self, const char* name,
                                                  int32_t* value,
                                                  sidl_BaseInterface *_ex)
      Set the int parameter associated with name
```

SIDL_C_INLINE_DECL int32_t

```
bHYPRE_SStructParCSRMatrix_GetDoubleValue (
                                                    bHYPRE_SStructParCSRMatrix
                                                    const char* name,
                                                    double* value,
                                                    sidl_BaseInterface
                                                    *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructParCSRMatrix_Setup ( bHYPRE_SStructParCSRMatrix
                                         self, bHYPRE_Vector b,
                                         bHYPRE_Vector x,
                                         sidl_BaseInterface *_ex)
      (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructParCSRMatrix_Apply ( bHYPRE_SStructParCSRMatrix
                                          self, bHYPRE_Vector b,
                                          bHYPRE_Vector* x,
                                          sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL_int32_t
bHYPRE_SStructParCSRMatrix_ApplyAdjoint (
                                                 bHYPRE_SStructParCSRMatrix
                                                 self, bHYPRE_Vector b,
                                                 bHYPRE_Vector* x,
                                                 sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_ex
      Cast method for interface and class type conversions
void*
bHYPRE_SStructParCSRMatrix_cast2 (void* obj, const char* type,
                                         sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
bHYPRE_SStructParCSRMatrix_exec ( bHYPRE_SStructParCSRMatrix
                                         self, const char* methodName,
                                         sidl_rmi_Call inArgs,
                                         sidl_rmi_Return outArgs,
                                         sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL char*
bHYPRE_SStructParCSRMatrix__getURL (
                                            bHYPRE\_SStructParCSRMatrix
                                            self, sidl_BaseInterface *_ex)
      Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL_void
```

bHYPRE_SStructParCSRMatrix__raddRef (bHYPRE_SStructParCSRMatrix self, sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance SIDL_C_INLINE_DECL_sidl_bool $bHYPRE_SStructParCSRMatrix__isRemote$ ($bHYPRE_SStructParCSRMatrix$ self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local sidl_bool bHYPRE_SStructParCSRMatrix__isLocal (bHYPRE_SStructParCSRMatrix self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local Cast method for interface and class type conversions $**_ex$ 4.7.14 RMI connector function for the class 102

4.7.1

$struct \ \ bHYPRE_SStructParCSRMatrix__object$

Symbol "bHYPRE.SStructParCSRMatrix" (version 1.0.0)

The SStructParCSR matrix class.

Objects of this type can be cast to SStructMatrixView or Operator objects using the __cast methods.

4.7.2

RMI connector function for the class.(addrefs)

4.7.3

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRMatrix_SetGraph (

bHYPRE_SStructParCSRMatrix self, bHYPRE_SStructGraph graph, sidl_BaseInterface *_ex)

Set the matrix graph. DEPRECATED Use Create

_ 4.7.4 _

int32_t bHYPRE_SStructParCSRMatrix_SetValues (

bHYPRE_SStructParCSRMatrix self, int32_t part, int32_t* index, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, sidl_BaseInterface *_ex)

Set matrix coefficients index by index.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type (there are no such restrictions for non-stencil entries).

If the matrix is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

4.7.5

$int32_t$

bHYPRE_SStructParCSRMatrix_SetBoxValues (

bHYPRE_SStructParCSRMatrix self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set matrix coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type (there are no such restrictions for non-stencil entries).

If the matrix is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

4.7.6

$int32_t$

bHYPRE_SStructParCSRMatrix_AddToValues (

bHYPRE_SStructParCSRMatrix self, int32_t part, int32_t* index, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, sidl_BaseInterface *_ex)

Add to matrix coefficients index by index.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type.

If the matrix is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

4.7.7 _

.

bHYPRE_SStructParCSRMatrix_AddToBoxValues (

bHYPRE_SStructParCSRMatrix self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, int32_t nentries, int32_t* entries, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Add to matrix coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of stencil type. Also, they must all represent couplings to the same variable type.

If the matrix is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

4.7.8

$\begin{array}{l} {\rm SIDL_C_INLINE_DECL\ int 32_t} \\ {\bf bHYPRE_SStructParCSRMatrix_SetSymmetric} \ (\end{array}$

bHYPRE_SStructParCSRMatrix self, int32_t part, int32_t var, int32_t to_var, int32_t symmetric, sidl_BaseInterface *_ex)

Define symmetry properties for the stencil entries in the matrix. The boolean argument symmetric is applied to stencil entries on part part that couple variable var to variable to_var. A value of -1 may be used for part, var, or to_var to specify "all". For example, if part and to_var are set to -1, then the boolean is applied to stencil entries on all parts that couple variable var to all other variables.

By default, matrices are assumed to be nonsymmetric. Significant storage savings can be made if the matrix is symmetric.

4.7.9

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRMatrix_Print (bHYPRE_SStructParCSRMatrix self, const char* filename, int32_t all, sidl_BaseInterface *_ex)

Print the matrix to file. This is mainly for debugging purposes.

4.7.10

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRMatrix_GetObject (bHYPRE_SStructParCSRMatrix self, sidl_BaseInterface* A, sidl_BaseInterface*_ex)

A semi-structured matrix or vector contains a Struct or IJ matrix or vector. GetObject returns it. The returned type is a sidl.BaseInterface. A cast must be used on the returned object to convert it into a known type.

4.7.11

SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructParCSRMatrix_SetCommunicator (
bHYPRE_SStructParCSRMatrix self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, Use Create()

4.7.12

SIDL_C_INLINE_DECL void bHYPRE_SStructParCSRMatrix_Destroy (bHYPRE_SStructParCSRMatrix self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

_ 4.7.13 _

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRMatrix_Assemble (bHYPRE_SStructParCSRMatrix self, sidl_BaseInterface *_ex)

Finalize the construction of an object before using, either for the first time or on subsequent uses. Initialize and Assemble always appear in a matched set, with Initialize preceding Assemble. Values can only be set in between a call to Initialize and Assemble.

_ 4.7.14 __

struct bHYPRE_SStructParCSRMatrix_object* bHYPRE_SStructParCSRMatrix_connectI const char * url sidl_bool ar struct sidl_BaseInterface_object **_ex

RMI connector function for the class. (no addref)

18

SemiStructured ParCSR Vector

Names		
4.8.1	struct bHYPRE_SStructParCSRVectorobject Symbol "bHYPRE	107
	_ex	
	Constructor function for the class	
	bHYPRE_SStructParCSRVector	
	bHYPRE_SStructParCSRVectorcreateRemote (const char * url, sidl_BaseInterface *_ex)	
	RMI constructor function for the class	
	bHYPRE_SStructParCSRVector bHYPRE_SStructParCSRVectorwrapObj (void * data,	
	sidl_BaseInterface *_ex)	
	$Wraps$ up the private data struct pointer (struct $bHYPRE_SStructParCSRVector__data$) passed in rather than running the constructor	
4.8.2	$b HYPRE_SStructParCSRVector$	
	$\mathbf{bHYPRE_SStructParCSRVector__connect} \ (\mathbf{const} \ \mathbf{char} \ ^*,$	
	sidl_BaseInterface *_ex)	105
	RMI connector function for the class	107
	bHYPRE_SStructParCSRVector bHYPRE_SStructParCSRVector_Create (bHYPRE_MPICommunicator	
	mpi_comm,	
	bHYPRE_SStructGrid grid, sidl_BaseInterface *_ex)	
	This function is the preferred way to create a SStruct ParCSR Vector	
	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_SStructParCSRVector_SetGrid (bHYPRE_SStructParCSRVector self, bHYPRE_SStructGrid grid,	
	sidl_BaseInterface *_ex)	
	Set the vector grid	
4.8.3	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRVector_SetValues (
	$b HYPRE_SStructParCSRVector$	
	self, int32_t part,	
	int32_t* index, int32_t dim,	
	int32_t var, double value, sidl_BaseInterface *_ex)	
	Set vector coefficients index by index	108
4.8.4	$\mathrm{int}32$ _t	
-		

	${ m bHYPRE_SStructParCSRVector_SetBoxValue}$	es (
		bHYPRE_SStructParCSRVector	
		self, int32_t part,	
		int32_t* ilower,	
		int32_t* iupper,	
		int32_t dim, int32_t var,	
		double* values,	
		int32 _{-t} nvalues,	
		,	
	Cat western coefficients a home at a time	$sidl_BaseInterface *_ex)$	100
	Set vector coefficients a box at a time		108
4.8.5	SIDL_C_INLINE_DECL int32_t		
	$b HYPRE_SStructParCSRVector_AddToValue$	es (
		$b HYPRE_SStructParCSRVector$	
		self, int32 _{-t} part,	
		int32_t* index,	
		int32_t dim, int32_t var,	
		double value,	
		sidl_BaseInterface *_ex)	
	Set vector coefficients index by index	,	108
	· · ·		100
4.8.6	$\mathrm{int}32$ _t		
	$b HYPRE_SStructParCSRVector_AddToBoxV$	(
		bHYPRE_SStructParCSRVec	ctor
		self, int32_t part,	
		int32_t* ilower,	
		int32_t* iupper,	
		int32_t dim,	
		int32_t var,	
		double* values,	
		int32_t nvalues,	
		sidl_BaseInterface	
		*_ex)	
	Set vector coefficients a box at a time		109
	SIDL_C_INLINE_DECL int32_t		
	bHYPRE_SStructParCSRVector_Gather (bH	YPRE_SStructParCSRVector	
	self,		
	Gather vector data before calling GetValues	sidi-Baselineriace (20x)	
	, and the second		
4.8.7	SIDL_C_INLINE_DECL int32_t		
	${\bf bHYPRE_SStructParCSRVector_GetValues} \ ($		
	1	OHYPRE_SStructParCSRVector	
	S	self, int32_t part,	
	i	nt32_t* index, int32_t dim,	
		nt32_t var, double* value,	
		sidl_BaseInterface *_ex)	
			109
			100
4.8.8	$\mathrm{int}32$ _t		

	${ m bHYPRE_SStructParCSRVector_GetBoxValues}$ (
	bHYPRE_SStructParCSRVector	•
	$self, int 32_t part,$	
	$int32_{-}t^{*}$ ilower,	
	$int32_{-}t^{*}$ iupper,	
	$int32_{-}t dim$, $int32_{-}t var$,	
	double* values,	
	int32t nvalues,	
	sidl_BaseInterface *_ex)	
	Get vector coefficients a box at a time	110
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRVector_SetComplex (
	$b HYPRE_SStructParCSRVector$	
	$\operatorname{self},$	
	$sidl_BaseInterface *_ex)$	
	Set the vector to be complex	
4.8.9	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRVector_Print (bHYPRE_SStructParCSRVector	
	self, const char* filename,	
	int32_t all, sidl_BaseInterface *_ex)	440
	Print the vector to file	110
4.8.10	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRVector_GetObject (
	bHYPRE_SStructParCSRVector self, sidl_BaseInterface* A, sidl_BaseInterface *_ex)	
	A semi-structured matrix or vector contains a Struct or IJ matrix or vector	
		110
4.8.11	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRVector_SetCommunicator (
	bHYPRE_SStructParCSRVe self,	ector
	bHYPRE_MPICommunicat	or
	mpi_comm,	01
	sidl_BaseInterface	
	*_ex)	
	Set the MPI Communicator	111
4.8.12	SIDL_C_INLINE_DECL_void	
4.0.12	bHYPRE_SStructParCSRVector_Destroy (bHYPRE_SStructParCSRVector self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	111
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructParCSRVector_Initialize (
	bHYPRE_SStructParCSRVector	
	self, sidl_BaseInterface *_ex)	
	Prepare an object for setting coefficient values, whether for the first time or subsequently	
4.8.13	SIDL_C_INLINE_DECL int32_t	

111
111
111
111

bHYPRE_SStructParCSRVector__getURL (bHYPRE_SStructParCSRVector self, sidl_BaseInterface *_ex) Get the URL of the Implementation of this object (for RMI) SIDL_C_INLINE_DECL void bHYPRE_SStructParCSRVector__raddRef ($bHYPRE_SStructParCSRVector$ self, sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance SIDL_C_INLINE_DECL sidl_bool bHYPRE_SStructParCSRVector__isRemote ($b HYPRE_SStructParCSRVector$ self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local $sidl_bool$ bHYPRE_SStructParCSRVector__isLocal (bHYPRE_SStructParCSRVector self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local **_ex Cast method for interface and class type conversions $**_e$ 4.8.15 RMI connector function for the class 112

4.8.1 .

struct bHYPRE_SStructParCSRVector_object

Symbol "bHYPRE.SStructParCSRVector" (version 1.0.0)

The SStructParCSR vector class.

Objects of this type can be cast to SStructVectorView or Vector objects using the __cast methods.

4.8.2

bHYPRE_SStructParCSRVector bHYPRE_SStructParCSRVector__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

4.8.3

SIDL_C_INLINE_DECL int32_t

bHYPRE_SStructParCSRVector_SetValues (bHYPRE_SStructParCSRVector self, int32_t part, int32_t* index, int32_t dim, int32_t var, double value, sidl_BaseInterface *_ex)

Set vector coefficients index by index.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

If the vector is complex, then value consists of a pair of doubles representing the real and imaginary parts of the complex value.

4.8.4

$int32_t$

bHYPRE_SStructParCSRVector_SetBoxValues (

bHYPRE_SStructParCSRVector self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set vector coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

If the vector is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

4.8.5

SIDL_C_INLINE_DECL int32_t

bHYPRE_SStructParCSRVector_AddToValues (

bHYPRE_SStructParCSRVector self, int32_t part, int32_t* index, int32_t dim, int32_t var, double value, sidl_BaseInterface *_ex)

Set vector coefficients index by index.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

If the vector is complex, then value consists of a pair of doubles representing the real and imaginary parts of the complex value.

4.8.6

$int32_t$

bHYPRE_SStructParCSRVector_AddToBoxValues (

bHYPRE_SStructParCSRVector self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Set vector coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

If the vector is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

4.8.7

SIDL_C_INLINE_DECL int32_t

bHYPRE_SStructParCSRVector_GetValues (

bHYPRE_SStructParCSRVector self, int32_t part, int32_t* index, int32_t dim, int32_t var, double* value, sidl_BaseInterface *_ex)

Get vector coefficients index by index.

NOTE: Users may only get values on processes that own the associated variables.

If the vector is complex, then value consists of a pair of doubles representing the real and imaginary parts of the complex value.

4.8.8

$int32_t$

$bHYPRE_SStructParCSRVector_GetBoxValues \ ($

bHYPRE_SStructParCSRVector self, int32_t part, int32_t* ilower, int32_t* iupper, int32_t dim, int32_t var, double* values, int32_t nvalues, sidl_BaseInterface *_ex)

Get vector coefficients a box at a time.

NOTE: Users may only get values on processes that own the associated variables.

If the vector is complex, then values consists of pairs of doubles representing the real and imaginary parts of each complex value.

4.8.9

SIDL_C_INLINE_DECL int32_t

bHYPRE_SStructParCSRVector_Print (bHYPRE_SStructParCSRVector self, const char* filename, int32_t all, sidl_BaseInterface *_ex)

Print the vector to file. This is mainly for debugging purposes.

_ 4.8.10 _

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRVector_GetObject (

bHYPRE_SStructParCSRVector self, sidl_BaseInterface* A, sidl_BaseInterface*_ex)

A semi-structured matrix or vector contains a Struct or IJ matrix or vector. GetObject returns it. The returned type is a sidl.BaseInterface. A cast must be used on the returned object to convert it into a known type.

4.8.11

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRVector_SetCommunicator (bHYPRE_SStructParCSRVector self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, Use Create()

4.8.12

SIDL_C_INLINE_DECL void bHYPRE_SStructParCSRVector_Destroy (bHYPRE_SStructParCSRVector self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

4.8.13

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRVector_Assemble (bHYPRE_SStructParCSRVector self, sidl_BaseInterface *_ex)

Finalize the construction of an object before using, either for the first time or on subsequent uses. Initialize and Assemble always appear in a matched set, with Initialize preceding Assemble. Values can only be set in between a call to Initialize and Assemble.

4.8.14

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructParCSRVector_Clone (bHYPRE_SStructParCSRVector self, bHYPRE_Vector* x, sidl_BaseInterface *_ex)

Create an x compatible with self. The new vector's data is not specified.

NOTE: When this method is used in an inherited class, the cloned Vector object can be cast to an object with the inherited class type.

_ 4.8.15 ___

RMI connector function for the class. (no addref)

. 5

Solver Interface

Names		
5.1	struct bHYPRE_Solver_object Symbol "bHYPRE	114
5.2	extern C bHYPRE_Solver bHYPRE_Solverconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	114
5.3	SIDL_C_INLINE_DECL int32_t bHYPRE_Solver_SetOperator (bHYPRE_Solver self,	115
5.4	SIDL_C_INLINE_DECL int32_t bHYPRE_Solver_SetTolerance (bHYPRE_Solver self, double tolerance, sidl_BaseInterface *_ex) (Optional) Set the convergence tolerance	115
5.5	SIDL_C_INLINE_DECL int32_t bHYPRE_Solver_SetMaxIterations (bHYPRE_Solver self, int32_t max_iterations, sidl_BaseInterface *_ex)	113
	(Optional) Set maximum number of iterations	115
5.6	SIDL_C_INLINE_DECL int32_t bHYPRE_Solver_SetLogging (bHYPRE_Solver self, int32_t level,	115
5.7	SIDL_C_INLINE_DECL int32_t bHYPRE_Solver_SetPrintLevel (bHYPRE_Solver self, int32_t level, sidl_BaseInterface *_ex) (Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	116
	SIDL_C_INLINE_DECL int32_t bHYPRE_Solver_GetNumIterations (bHYPRE_Solver self,	
	SIDL_C_INLINE_DECL int32_t bHYPRE_Solver_GetRelResidualNorm (bHYPRE_Solver self,	
	_ex Cast method for interface and class type conversions	
	void*	

	bHYPRE_Solvercast2 (void* obj, const char* type, sidl_BaseInterface *_ex) String cast method for interface and class type conversions	
	SIDL_C_INLINE_DECL void bHYPRE_Solver_exec (bHYPRE_Solver self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex) Select and execute a method by name	
	SIDL_C_INLINE_DECL_char* bHYPRE_SolvergetURL (bHYPRE_Solver self, sidl_BaseInterface *_ex) Get the URL of the Implementation of this object (for RMI)	
	SIDL_C_INLINE_DECL_void bHYPRE_Solver_raddRef (bHYPRE_Solver self, sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance	
	SIDL_C_INLINE_DECL_sidl_bool bHYPRE_SolverisRemote (bHYPRE_Solver self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local	
	sidl_bool bHYPRE_SolverisLocal (bHYPRE_Solver self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local	
	**_ex Cast method for interface and class type conversions	
5.8	**_ex RMI connector function for the class	116
5.9	Identity Solver (does nothing)	
5.10	Hybrid Solver	116
		123

5.1

 $struct \ \ bHYPRE_Solver__object$

Symbol "bHYPRE.Solver" (version 1.0.0)

5.2

extern C bHYPRE_Solver ${\bf bHYPRE_Solver_connect}$ (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

_ 5.3 _

SIDL_C_INLINE_DECL int32_t bHYPRE_Solver_SetOperator (bHYPRE_Solver self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

_ 5.4 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_Solver_SetTolerance (bHYPRE_Solver self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

5.5

SIDL_C_INLINE_DECL int32_t bHYPRE_Solver_SetMaxIterations (bHYPRE_Solver_self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

5.6

SIDL_C_INLINE_DECL int32_t bHYPRE_Solver_SetLogging (bHYPRE_Solver self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

_ 5.7 _

SIDL_C_INLINE_DECL int32_t bHYPRE_Solver_SetPrintLevel (bHYPRE_Solver self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

_ 5.8 _

struct bHYPRE_Solver__object* bHYPRE_Solver__connectI const char * url sidl_bool ar struct sidl_BaseInterface__object **_ex

RMI connector function for the class. (no addref)

_ 5.9 _

Identity Solver (does nothing)

Names

5.9.1

_ex

Constructor function for the class

bHYPRE_IdentitySolver

 $\mathbf{bHYPRE_IdentitySolver__createRemote} \ (\mathbf{const} \ \mathbf{char} \ ^* \ \mathbf{url},$

sidl_BaseInterface *_ex)

RMI constructor function for the class

bHYPRE_IdentitySolver

	bHYPRE_IdentitySolverwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_IdentitySolverdata) passed in rather than running the con- structor	
5.9.2	bHYPRE_IdentitySolver bHYPRE_IdentitySolver_connect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	121
	bHYPRE_IdentitySolver_Create (bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)	
	This function is the preferred way to create an Identity (null) solver	
5.9.3	SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_SetOperator (bHYPRE_IdentitySolver self, bHYPRE_Operator A, sidl_BaseInterface *_ex)	
	Set the operator for the linear system being solved	121
5.9.4	SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_SetTolerance (bHYPRE_IdentitySolver self, double tolerance,	
	sidl_BaseInterface *_ex) (Optional) Set the convergence tolerance	121
T 0 F		121
5.9.5	SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_SetMaxIterations (bHYPRE_IdentitySolver self, int32_t max_iterations, sidl_BaseInterface *_ex)	
	(Optional) Set maximum number of iterations	121
5.9.6	SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_SetLogging (bHYPRE_IdentitySolver self,	
	(Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	122
5.9.7	SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_SetPrintLevel (bHYPRE_IdentitySolver self, int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	122
	SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_GetNumIterations (bHYPRE_IdentitySolver self, int32_t* num_iterations, sidl_BaseInterface *_ex)	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_IdentitySolver_GetRelResidualNorm (bHYPRE_IdentitySolver self, double* norm, sidl_BaseInterface *_ex)	
	(Optional) Return the norm of the relative residual	
5.9.8	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_IdentitySolver_SetCommunicator (bHYPRE_IdentitySolver self, bHYPRE_MPICommunicator	
	$\mathrm{mpi_comm},$	
	sidl_BaseInterface *_ex)	
	Set the MPI Communicator	122
5.9.9	SIDL_C_INLINE_DECL_void bHYPRE_IdentitySolver_Destroy (bHYPRE_IdentitySolver self,	
	sidl_BaseInterface *_ex) The Destroy function doesn't necessarily destroy anything	122
	SIDL_C_INLINE_DECL int32_t	122
	bHYPRE_IdentitySolver_SetIntParameter (bHYPRE_IdentitySolver self, const char* name, int32_t value,	
	sidl_BaseInterface *_ex)	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_SetDoubleParameter (bHYPRE_IdentitySolver self, const char* name, double value,	
	sidl_BaseInterface *_ex)	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_SetStringParameter (bHYPRE_IdentitySolver	
	Set the string parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_SetIntArray1Parameter (bHYPRE_IdentitySolver self, const char* name, int32_t* value,	
	int32t nvalues,	
	sidl_BaseInterface *_ex) Set the int 1-D array parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_IdentitySolver_SetIntArray2Parameter (
	bHYPRE_IdentitySolver self, const char* name, struct sidl_intarray* value, sidl_BaseInterface *_ex)	
	Set the int 2-D array parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_IdentitySolver_SetDoubleArray1Parameter (
                                                         bHYPRE_IdentitySolver
                                                         const char* name,
                                                         double* value,
                                                         int32_t nvalues,
                                                         sidl_BaseInterface
                                                         *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_IdentitySolver_SetDoubleArray2Parameter (
                                                         {\it bHYPRE\_IdentitySolver}
                                                         self,
                                                         const char* name,
                                                         struct
                                                         sidl_double_array*
                                                         value,
                                                         sidl_BaseInterface
                                                         *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_IdentitySolver_GetIntValue ( bHYPRE_IdentitySolver self,
                                         const char* name, int32_t* value,
                                         sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_IdentitySolver_GetDoubleValue ( bHYPRE_IdentitySolver self,
                                             const char* name.
                                             double* value,
                                             sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_IdentitySolver_Setup ( bHYPRE_IdentitySolver self,
                                  bHYPRE_Vector b, bHYPRE_Vector x,
                                 sidl_BaseInterface *_ex)
       (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_IdentitySolver_Apply ( bHYPRE_IdentitySolver self,
                                  bHYPRE_Vector b, bHYPRE_Vector* x,
                                  sidl_BaseInterface *_ex)
       Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_IdentitySolver_ApplyAdjoint ( bHYPRE_IdentitySolver self,
                                          bHYPRE_Vector b,
                                          bHYPRE_Vector* x,
                                          sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
```

_ex

Cast method for interface and class type conversions

void*

bHYPRE_IdentitySolver__cast2 (void* obj, const char* type, sidl_BaseInterface *_ex)

String cast method for interface and class type conversions

SIDL_C_INLINE_DECL void

bHYPRE_IdentitySolver__exec (bHYPRE_IdentitySolver self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex)

Select and execute a method by name

SIDL_C_INLINE_DECL char*

bHYPRE_IdentitySolver__getURL (bHYPRE_IdentitySolver self, sidl_BaseInterface *_ex)

Get the URL of the Implementation of this object (for RMI)

SIDL_C_INLINE_DECL void

bHYPRE_IdentitySolver__raddRef (bHYPRE_IdentitySolver self, sidl_BaseInterface *_ex)

On a remote object, addrefs the remote instance

SIDL_C_INLINE_DECL sidl_bool

bHYPRE_IdentitySolver__isRemote (bHYPRE_IdentitySolver self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

 $sidl_bool$

bHYPRE_IdentitySolver__isLocal (bHYPRE_IdentitySolver self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

**_ex

Cast method for interface and class type conversions

5.9.10 **_ex

5.9.1 .

struct bHYPRE_IdentitySolver_object

Symbol "bHYPRE.IdentitySolver" (version 1.0.0)

Identity solver, just solves an identity matrix, for when you don't really want a preconditioner

Objects of this type can be cast to Solver objects using the __cast methods.

5.9.2

bHYPRE_IdentitySolver

bHYPRE_IdentitySolver_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

_ 5.9.3 __

SIDL_C_INLINE_DECL int32_t
bHYPRE_IdentitySolver_SetOperator (bHYPRE_IdentitySolver self, bHYPRE_Operator A, sidl_BaseInterface $*_ex$)

Set the operator for the linear system being solved. DEPRECATED. use Create

__ 5.9.4 _____

SIDL_C_INLINE_DECL int32_t

bHYPRE_IdentitySolver_SetTolerance (bHYPRE_IdentitySolver self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

5.9.5

SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_SetMaxIterations (bHYPRE_IdentitySolver self,

bHYPRE_IdentitySolver_SetMaxIterations (bHYPRE_IdentitySolver self int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

5.9.6

SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_SetLogging (bHYPRE_IdentitySolver self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

 $_$ 5.9.7 $_$

SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_SetPrintLevel (bHYPRE_IdentitySolver self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

 $_{-}$ 5.9.8 $_{-}$

SIDL_C_INLINE_DECL int32_t bHYPRE_IdentitySolver_SetCommunicator (bHYPRE_IdentitySolver self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

 $_$ 5.9.9 $_$

SIDL_C_INLINE_DECL void bHYPRE_IdentitySolver_Destroy (bHYPRE_IdentitySolver self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

5.9.10

RMI connector function for the class. (no addref)

_ 5.10 _

Hybrid Solver

Names		
5.10.1	struct bHYPRE_Hybridobject Symbol "bHYPRE	126
	$_{-\mathbf{ex}}$ Constructor function for the class	
	bHYPRE_Hybrid bHYPRE_HybridcreateRemote (const char * url, sidl_BaseInterface *_ex) RMI constructor function for the class	
	bHYPRE_Hybrid bHYPRE_HybridwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_Hybriddata) passed in rather than running the constructor	
5.10.2	bHYPRE_Hybrid bHYPRE_Hybridconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	127
	bHYPRE_Hybrid bHYPRE_Hybrid_Create (bHYPRE_MPICommunicator mpi_comm,	
	SIDL_C_INLINE_DECL int32_t bHYPRE_Hybrid_GetFirstSolver (bHYPRE_Hybrid self,	
	$Method: \ GetFirstSolver[]$	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_Hybrid_GetSecondSolver (bHYPRE_Hybrid self, bHYPRE_PreconditionedSolver* SecondSolver, sidl_BaseInterface *_ex)	
	$Method:\ GetSecondSolver[]$	
5.10.3	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_Hybrid_SetOperator (bHYPRE_Hybrid self, bHYPRE_Operator A, sidl_BaseInterface *_ex)	
	Set the operator for the linear system being solved	127
5.10.4	SIDL_C_INLINE_DECL int32_t bHYPRE_Hybrid_SetTolerance (bHYPRE_Hybrid self, double tolerance, sidl_BaseInterface *_ex)	
	(Optional) Set the convergence tolerance	127
5.10.5	SIDL_C_INLINE_DECL int32_t bHYPRE_Hybrid_SetMaxIterations (bHYPRE_Hybrid self,	
	(Optional) Set maximum number of iterations	128
5.10.6	SIDL_C_INLINE_DECL int32_t bHYPRE_Hybrid_SetLogging (bHYPRE_Hybrid self, int32_t level,	
	(Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	128
5.10.7	SIDL_C_INLINE_DECL int32_t bHYPRE_Hybrid_SetPrintLevel (bHYPRE_Hybrid self, int32_t level,	
	(Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	128
	SIDL_C_INLINE_DECL int32_t bHYPRE_Hybrid_GetNumIterations (bHYPRE_Hybrid self,	
	SIDL_C_INLINE_DECL int32_t bHYPRE_Hybrid_GetRelResidualNorm (bHYPRE_Hybrid self,	
5.10.8	(Optional) Return the norm of the relative residual SIDL_C_INLINE_DECL int32_t bHYPRE_Hybrid_SetCommunicator (bHYPRE_Hybrid self,	
	Set the MPI Communicator	128
5.10.9	SIDL_C_INLINE_DECL void bHYPRE_Hybrid_Destroy (bHYPRE_Hybrid self, sidl_BaseInterface *_ex) The Destroy function doesn't necessarily destroy anything	129
	SIDL_C_INLINE_DECL_int32_t bHYPRE_Hybrid_SetIntParameter (bHYPRE_Hybrid self,	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_Hybrid_SetDoubleParameter ( bHYPRE_Hybrid self.
                                         const char* name, double value,
                                         sidl_BaseInterface *_ex)
      Set the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Hybrid_SetStringParameter ( bHYPRE_Hybrid self,
                                        const char* name,
                                        const char* value,
                                        sidl_BaseInterface *_ex)
      Set the string parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Hybrid_SetIntArray1Parameter ( bHYPRE_Hybrid self,
                                             const char* name,
                                            int32_t* value, int32_t nvalues,
                                            sidl_BaseInterface *_ex)
      Set the int 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Hybrid_SetIntArray2Parameter ( bHYPRE_Hybrid self,
                                            const char* name,
                                            struct sidl_int_array* value,
                                            sidl_BaseInterface *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Hybrid_SetDoubleArray1Parameter ( bHYPRE_Hybrid self,
                                                 const char* name.
                                                 double* value,
                                                 int32_t nvalues,
                                                 sidl_BaseInterface *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Hybrid_SetDoubleArray2Parameter ( bHYPRE_Hybrid self,
                                                 const char* name, struct
                                                 sidl_double_array* value,
                                                 sidl_BaseInterface *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Hybrid_GetIntValue ( bHYPRE_Hybrid self, const char* name,
                                int32_t* value, sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Hybrid_GetDoubleValue ( bHYPRE_Hybrid self,
                                     const char* name, double* value,
                                     sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Hybrid_Setup ( bHYPRE_Hybrid self, bHYPRE_Vector b,
                          bHYPRE_Vector x, sidl_BaseInterface *_ex)
      (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
```

SIDL_C_INLINE_DECL int32_t

```
bHYPRE_Hybrid_Apply ( bHYPRE_Hybrid self, bHYPRE_Vector b,
                                       bHYPRE_Vector* x, sidl_BaseInterface *_ex)
                   Apply the operator to b, returning x
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_Hybrid_ApplyAdjoint ( bHYPRE_Hybrid self,
                                               bHYPRE_Vector b, bHYPRE_Vector* x,
                                               sidl_BaseInterface *_ex)
                   Apply the adjoint of the operator to b, returning x
            _{\mathbf{ex}}
                   Cast method for interface and class type conversions
            void*
            bHYPRE_Hybrid__cast2 (void* obj, const char* type,
                                       sidl_BaseInterface *_ex)
                   String cast method for interface and class type conversions
            SIDL_C_INLINE_DECL void
            bHYPRE_Hybrid_exec ( bHYPRE_Hybrid self, const char* methodName,
                                      sidl_rmi_Call inArgs, sidl_rmi_Return outArgs,
                                      sidl_BaseInterface *_ex)
                   Select and execute a method by name
            SIDL_C_INLINE_DECL char*
            bHYPRE_Hybrid__getURL ( bHYPRE_Hybrid self, sidl_BaseInterface *_ex)
                   Get the URL of the Implementation of this object (for RMI)
            SIDL_C_INLINE_DECL void
            bHYPRE_Hybrid __raddRef ( bHYPRE_Hybrid self, sidl_BaseInterface *_ex)
                   On a remote object, addrefs the remote instance
            SIDL_C_INLINE_DECL sidl_bool
            bHYPRE_Hybrid_isRemote ( bHYPRE_Hybrid self,
                                           sidl_BaseInterface *_ex)
                   TRUE if this object is remote, false if local
            sidl\_bool
            bHYPRE_Hybrid__isLocal ( bHYPRE_Hybrid self, sidl_BaseInterface *_ex)
                   TRUE if this object is remote, false if local
            **_ex
                   Cast method for interface and class type conversions
            **_ex
5.10.10
                   RMI connector function for the class ......
                                                                                             129
```

5.10.1

 $struct\ bHYPRE_Hybrid__object$

Symbol "bHYPRE.Hybrid" (version 1.0.0)

Hybrid solver first tries to solve with the specified Krylov solver, preconditioned by If that fails to converge, it will try again with the user-specified

Specify the preconditioner by calling SecondSolver's SetPreconditioner method. If no preconditioner is specified (equivalently, if the preconditioner for SecondSolver is IdentitySolver), the preconditioner for the second try will be one of the following defaults. StructMatrix: SMG. other matrix types: not implemented

The Hybrid solver's Setup method will call Setup on KrylovSolver, so the user should not call Setup on KrylovSolver.

5.10.2

bHYPRE_Hybrid bHYPRE_Hybrid__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

_ 5.10.3 ____

SIDL_C_INLINE_DECL int32_t bHYPRE_Hybrid_SetOperator (bHYPRE_Hybrid self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

5.10.4

SIDL_C_INLINE_DECL int32_t **bHYPRE_Hybrid_SetTolerance** (bHYPRE_Hybrid self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

5.10.5

SIDL_C_INLINE_DECL int32_t bHYPRE_Hybrid_SetMaxIterations (bHYPRE_Hybrid self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

__ 5.10.6 ____

SIDL_C_INLINE_DECL int32_t bHYPRE_Hybrid_SetLogging (bHYPRE_Hybrid self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the $logging\ level$, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

5.10.7

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

__ 5.10.8 ____

SIDL_C_INLINE_DECL int32_t bHYPRE_Hybrid_SetCommunicator (bHYPRE_Hybrid self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

5.10.9

SIDL_C_INLINE_DECL void bHYPRE_Hybrid_Destroy (bHYPRE_Hybrid self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

5.10.10

RMI connector function for the class. (no addref)

6

ParCSR Matrix Solvers

Names		
6.1	ParCSRDiagScale Solver	
		130
6.2	ParCSR BoomerAMG Solver	
		137
6.3	ParCSR Euclid Solver	
		146
6.4	ParCSR Schwarz Solver	
		152
6.5	ParCSR ParaSails Solver	
		158
6.6	ParCSR Pilut Solver	
		164

These solvers use matrix/vector storage schemes that are tailored for general sparse matrix systems.

6.1

ParCSRDiagScale Solver

Names 6.1.1 $struct \ \ bHYPRE_ParCSRDiagScale__object$ Symbol "bHYPRE 135 _ex Constructor function for the class $bHYPRE_ParCSRDiagScale$ bHYPRE_ParCSRDiagScale__createRemote (const char * url, sidl_BaseInterface *_ex) RMI constructor function for the class $bHYPRE_ParCSRDiagScale$ bHYPRE_ParCSRDiagScale__wrapObj (void * data, sidl_BaseInterface *_ex) Wrapstheprivatedatastructpointer(struct $bHYPRE_ParCSRDiagScale__data) \hspace{0.2cm} passed \hspace{0.2cm} in \hspace{0.2cm} rather \hspace{0.2cm} than \hspace{0.2cm} running \hspace{0.2cm} the \hspace{0.2cm} and \hspace{$ constructor6.1.2 $bHYPRE_ParCSRDiagScale$

	bHYPRE_ParCSRDiagScaleconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	135
	bHYPRE_ParCSRDiagScale bHYPRE_ParCSRDiagScale_Create (bHYPRE_MPICommunicator	
	mpi_comm, bHYPRE_IJParCSRMatrix A,	
	sidl_BaseInterface *_ex) This function is the preferred way to create a ParCSR DiagScale solver	
6.1.3	SIDL_C_INLINE_DECL_int32_t bHYPRE_ParCSRDiagScale_SetOperator (bHYPRE_ParCSRDiagScale self, bHYPRE_Operator A, sidl_BaseInterface *_ex)	
	Set the operator for the linear system being solved	135
6.1.4	SIDL_C_INLINE_DECL int32_t bHYPRE_ParCSRDiagScale_SetTolerance (bHYPRE_ParCSRDiagScale self, double tolerance, sidl_BaseInterface *_ex)	
	(Optional) Set the convergence tolerance	135
6.1.5	SIDL_C_INLINE_DECL int32_t bHYPRE_ParCSRDiagScale_SetMaxIterations (
	(Optional) Set maximum number of iterations	136
6.1.6	SIDL_C_INLINE_DECL_int32_t bHYPRE_ParCSRDiagScale_SetLogging (bHYPRE_ParCSRDiagScale self, int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	136
6.1.7	SIDL_C_INLINE_DECL int32_t bHYPRE_ParCSRDiagScale_SetPrintLevel (bHYPRE_ParCSRDiagScale self, int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	136
	SIDL_C_INLINE_DECL int32_t bHYPRE_ParCSRDiagScale_GetNumIterations (
	bHYPRE_ParCSRDiagScale self, int32_t* num_iterations, sidl_BaseInterface *_ex)	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE\_ParCSRDiagScale\_GetRelResidualNorm (
                                                               bHYPRE_ParCSRDiagScale
                                                               self, double* norm,
                                                               sidl_BaseInterface
                                                               *_ex)
                  (Optional) Return the norm of the relative residual
6.1.8
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_ParCSRDiagScale_SetCommunicator (
                                                            bHYPRE_ParCSRDiagScale
                                                            self,
                                                            b HYPRE\_MPIC ommunicator
                                                            mpi_comm,
                                                            sidl_BaseInterface *_ex)
                  Set the MPI Communicator .....
                                                                                         136
6.1.9
            SIDL_C_INLINE_DECL void
            bHYPRE_ParCSRDiagScale_Destroy ( bHYPRE_ParCSRDiagScale self,
                                                  sidl_BaseInterface *_ex)
                  The Destroy function doesn't necessarily destroy anything .....
                                                                                         137
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_ParCSRDiagScale_SetIntParameter (
                                                          bHYPRE\_ParCSRDiagScale
                                                          self, const char* name,
                                                          int32_t value,
                                                          sidl_BaseInterface *_ex)
                  Set the int parameter associated with name
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_ParCSRDiagScale_SetDoubleParameter (
                                                              bHYPRE_ParCSRDiagScale
                                                              self,
                                                              const char* name,
                                                              double value,
                                                              sidl_BaseInterface *_ex)
                  Set the double parameter associated with name
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_ParCSRDiagScale_SetStringParameter (
                                                              bHYPRE_ParCSRDiagScale
                                                              self, const char* name,
                                                              const char* value,
                                                              sidl_BaseInterface *_ex)
                  Set the string parameter associated with name
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_ParCSRDiagScale_SetIntArray1Parameter (
                                                                 bHYPRE\_ParCSRDiagScale
                                                                 const char* name,
                                                                 int32_t* value,
                                                                 int32_t nvalues,
                                                                 sidl_BaseInterface
                                                                 *_ex)
                  Set the int 1-D array parameter associated with name
            SIDL_C_INLINE_DECL int32_t
```

```
bHYPRE_ParCSRDiagScale_SetIntArray2Parameter (
                                                       bHYPRE_ParCSRDiagScale
                                                       const char* name,
                                                       struct
                                                       sidl_int_array*
                                                       value.
                                                       sidl_BaseInterface
                                                        *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE\_ParCSRDiagScale\_SetDoubleArray1Parameter\ (
                                                            bHYPRE_ParCSRDiagScale
                                                            self, const
                                                            char* name,
                                                            double* value,
                                                            int32_t nvalues,
                                                            sidl\_BaseInterface
                                                            *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_ParCSRDiagScale_SetDoubleArray2Parameter (
                                                            bHYPRE_ParCSRDiagScale
                                                            self, const
                                                            char* name,
                                                            struct
                                                            sidl_double_array*
                                                            value.
                                                            sidl_BaseInterface
                                                            *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_ParCSRDiagScale_GetIntValue ( bHYPRE_ParCSRDiagScale
                                            self, const char* name,
                                            int32_t* value,
                                            sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_ParCSRDiagScale_GetDoubleValue (
                                                bHYPRE_ParCSRDiagScale
                                                self, const char* name,
                                                double* value,
                                                sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_ParCSRDiagScale_Setup ( bHYPRE_ParCSRDiagScale self,
                                     bHYPRE_Vector b, bHYPRE_Vector x,
                                     sidl_BaseInterface *_ex)
       (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
```

```
bHYPRE_ParCSRDiagScale_Apply ( bHYPRE_ParCSRDiagScale self,
                                     bHYPRE_Vector b.
                                     bHYPRE_Vector* x,
                                     sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_ParCSRDiagScale_ApplyAdjoint ( bHYPRE_ParCSRDiagScale
                                             self, bHYPRE_Vector b,
                                             bHYPRE_Vector* x,
                                             sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_ex
      Cast method for interface and class type conversions
void*
bHYPRE_ParCSRDiagScale__cast2 (void* obj, const char* type,
                                     sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
bHYPRE_ParCSRDiagScale__exec ( bHYPRE_ParCSRDiagScale self,
                                    const char* methodName,
                                    sidl_rmi_Call inArgs,
                                    sidl_rmi_Return outArgs,
                                    sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL char*
bHYPRE_ParCSRDiagScale__getURL ( bHYPRE_ParCSRDiagScale self,
                                       sidl_BaseInterface *_ex)
      Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL_void
bHYPRE_ParCSRDiagScale__raddRef ( bHYPRE_ParCSRDiagScale self,
                                        sidl_BaseInterface *_ex)
      On a remote object, addrefs the remote instance
SIDL_C_INLINE_DECL sidl_bool
bHYPRE_ParCSRDiagScale__isRemote ( bHYPRE_ParCSRDiagScale self,
                                         sidl_BaseInterface *_ex)
      TRUE if this object is remote, false if local
sidl_bool
bHYPRE_ParCSRDiagScale__isLocal ( bHYPRE_ParCSRDiagScale self,
                                       sidl_BaseInterface *_ex)
       TRUE if this object is remote, false if local
**_ex
      Cast method for interface and class type conversions
**_ex
      RMI connector function for the class ......
                                                                               137
```

6.1.10

 $_{-}$ 6.1.1 $_{-}$

struct bHYPRE_ParCSRDiagScale_object

Symbol "bHYPRE.ParCSRDiagScale" (version 1.0.0)

Diagonal scaling preconditioner for ParCSR matrix class.

Objects of this type can be cast to Solver objects using the __cast methods.

 $_{-}$ 6.1.2 $_{-}$

bHYPRE_ParCSRDiagScale

bHYPRE_ParCSRDiagScale__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

6.1.3

SIDL_C_INLINE_DECL int32_t bHYPRE_ParCSRDiagScale_SetOperator (bHYPRE_ParCSRDiagScale self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

6.1.4

SIDL_C_INLINE_DECL int32_t

bHYPRE_ParCSRDiagScale_SetTolerance (bHYPRE_ParCSRDiagScale self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter $\,$

6.1.5

SIDL_C_INLINE_DECL int32_t bHYPRE_ParCSRDiagScale_SetMaxIterations (

bHYPRE_ParCSRDiagScale self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

6.1.6

SIDL_C_INLINE_DECL int32_t bHYPRE_ParCSRDiagScale_SetLogging (bHYPRE_ParCSRDiagScale self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the $logging\ level$, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

__ 6.1.7 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_ParCSRDiagScale_SetPrintLevel (bHYPRE_ParCSRDiagScale self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

__ 6.1.8 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_ParCSRDiagScale_SetCommunicator (bHYPRE_ParCSRDiagScale self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

6.1.9

SIDL_C_INLINE_DECL_void bHYPRE_ParCSRDiagScale_Destroy (bHYPRE_ParCSRDiagScale self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

6.1.10

struct bHYPRE_ParCSRDiagScale__object* bHYPRE_ParCSRDiagScale__connectI const char * url sidl_bool ar struct sidl_BaseInterface__object ***_ex

RMI connector function for the class. (no addref)

6.2

ParCSR BoomerAMG Solver

Names		
6.2.1	struct bHYPRE_BoomerAMGobject Symbol "bHYPRE	141
	_ex Constructor function for the class	
	bHYPRE_BoomerAMG bHYPRE_BoomerAMGcreateRemote (const char * url,	
	bHYPRE_BoomerAMG bHYPRE_BoomerAMGwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_BoomerAMGdata) passed in rather than running the constructor	
6.2.2	bHYPRE_BoomerAMG bHYPRE_BoomerAMGconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	144
	bHYPRE_BoomerAMG	

	bHYPRE_JParCSRMatrix A,	
	sidl_BaseInterface *_ex)	
	This function is the preferred way to create a BoomerAMG solver	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_BoomerAMG_SetLevelRelaxWt (bHYPRE_BoomerAMG self, double relax_wt, int32_t level, sidl_BaseInterface *_ex)	
	$Method:\ SetLevelRelaxWt[]$	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_BoomerAMG_InitGridRelaxation (bHYPRE_BoomerAMG self, struct sidl_intarray** num_grid_sweeps, struct sidl_intarray** grid_relax_type, struct sidl_intarray** grid_relax_points, int32_t coarsen_type, struct sidl_doublearray** relax_weights, int32_t max_levels,	
	sidl_BaseInterface *_ex) Method: InitGridRelaxation[]	
5.2.3	SIDL_C_INLINE_DECL int32_t	
).2.3	bHYPRE_BoomerAMG_SetOperator (bHYPRE_BoomerAMG self, bHYPRE_Operator A, sidl_BaseInterface *_ex)	1.4.
	Set the operator for the linear system being solved	144
3.2.4	SIDL_C_INLINE_DECL int32_t bHYPRE_BoomerAMG_SetTolerance (bHYPRE_BoomerAMG self,	
	(Optional) Set the convergence tolerance	144
6.2.5	SIDL_C_INLINE_DECL int32_t	
,. <u>=</u> 0	bHYPRE_BoomerAMG_SetMaxIterations (bHYPRE_BoomerAMG self, int32_t max_iterations, sidl_BaseInterface *_ex)	
	(Optional) Set maximum number of iterations	144
5.2.6	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_BoomerAMG_SetLogging (bHYPRE_BoomerAMG self, int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	14
3.2.7	SIDL_C_INLINE_DECL int32_t bHYPRE_BoomerAMG_SetPrintLevel (bHYPRE_BoomerAMG self, int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	145
	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_BoomerAMG_GetNumIterations (bHYPRE_BoomerAMG self, int32_t* num_iterations, sidl_BaseInterface *_ex)	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_BoomerAMG_GetRelResidualNorm (bHYPRE_BoomerAMG self, double* norm, sidl_BaseInterface *_ex)	
	(Optional) Return the norm of the relative residual	
6.2.8	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_BoomerAMG_SetCommunicator (bHYPRE_BoomerAMG self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)	
	Set the MPI Communicator	145
6.2.9	SIDL_C_INLINE_DECL_void bHYPRE_BoomerAMG_Destroy (bHYPRE_BoomerAMG self,	
	The Destroy function doesn't necessarily destroy anything	145
	SIDL_C_INLINE_DECL_int32_t bHYPRE_BoomerAMG_SetIntParameter (bHYPRE_BoomerAMG self,	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_BoomerAMG_SetDoubleParameter (bHYPRE_BoomerAMG self, const char* name, double value, sidl_BaseInterface *_ex)	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_BoomerAMG_SetStringParameter (bHYPRE_BoomerAMG self, const char* name, const char* value, sidl_BaseInterface *_ex)	
	Set the string parameter associated with name	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_BoomerAMG_SetIntArray1Parameter (bHYPRE_BoomerAMG self, const char* name, int32_t* value, int32_t nvalues, sidl_BaseInterface *_ex)	
	Set the int 1-D array parameter associated with name	
	SIDL_C_INLINE_DECL_int32_t	

```
bHYPRE_BoomerAMG_SetIntArray2Parameter ( bHYPRE_BoomerAMG
                                                  self, const char* name,
                                                  struct sidl_int_array*
                                                  value.
                                                  sidl_BaseInterface *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_BoomerAMG_SetDoubleArray1Parameter (
                                                      bHYPRE_BoomerAMG
                                                      self.
                                                      const char* name,
                                                      double* value,
                                                      int32_t nvalues,
                                                      sidl_BaseInterface
                                                      *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_BoomerAMG_SetDoubleArray2Parameter (
                                                      bHYPRE_BoomerAMG
                                                      self.
                                                      const char* name,
                                                      struct
                                                      sidl_double_array*
                                                      value.
                                                      sidl\_BaseInterface
                                                      *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_BoomerAMG_GetIntValue ( bHYPRE_BoomerAMG self,
                                      const char* name, int32_t* value,
                                      sidl\_BaseInterface *\_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_BoomerAMG_GetDoubleValue ( bHYPRE_BoomerAMG self,
                                          const char* name.
                                           double* value.
                                          sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_BoomerAMG_Setup ( bHYPRE_BoomerAMG self,
                                bHYPRE_Vector b, bHYPRE_Vector x,
                                sidl_BaseInterface *_ex)
      (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_BoomerAMG_Apply ( bHYPRE_BoomerAMG self,
                                bHYPRE_Vector b, bHYPRE_Vector* x,
                                sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
```

```
bHYPRE_BoomerAMG_ApplyAdjoint ( bHYPRE_BoomerAMG self,
                                        bHYPRE_Vector b,
                                        bHYPRE_Vector* x,
                                        sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_ex
      Cast method for interface and class type conversions
void*
bHYPRE_BoomerAMG__cast2 (void* obj, const char* type,
                                sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
bHYPRE_BoomerAMG__exec ( bHYPRE_BoomerAMG self,
                               const char* methodName,
                               sidl_rmi_Call inArgs,
                               sidl_rmi_Return outArgs,
                               sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL char*
bHYPRE_BoomerAMG__getURL ( bHYPRE_BoomerAMG self,
                                   sidl_BaseInterface *_ex)
      Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL void
bHYPRE_BoomerAMG_raddRef ( bHYPRE_BoomerAMG self,
                                   sidl_BaseInterface *_ex)
      On a remote object, addrefs the remote instance
SIDL_C_INLINE_DECL_sidl_bool
bHYPRE_BoomerAMG__isRemote ( bHYPRE_BoomerAMG self,
                                    sidl_BaseInterface *_ex)
      TRUE if this object is remote, false if local
sidl_bool
bHYPRE_BoomerAMG__isLocal ( bHYPRE_BoomerAMG self,
                                 sidl_BaseInterface *_ex)
      TRUE if this object is remote, false if local
**_ex
      Cast method for interface and class type conversions
**_ex
      RMI connector function for the class .....
                                                                              146
```

 $_{-}$ 6.2.1 $_{-}$

6.2.10

struct bHYPRE_BoomerAMG__object

Symbol "bHYPRE.BoomerAMG" (version 1.0.0)

Algebraic multigrid solver, based on classical Ruge-Stueben.

BoomerAMG requires an IJParCSR matrix

The following optional parameters are available and may be set using the appropriate Parameter function (as indicated in parentheses):

MaxLevels (Int) - maximum number of multigrid levels.

StrongThreshold (Double) - AMG strength threshold.

MaxRowSum (Double) -

CoarsenType (Int) - type of parallel coarsening algorithm used.

MeasureType (Int) - type of measure used; local or global.

CycleType (Int) - type of cycle used; a V-cycle (default) or a W-cycle.

NumGridSweeps (IntArray 1D) - number of sweeps for fine and coarse grid, up and down cycle. DEP-RECATED: Use NumSweeps or Cycle?NumSweeps instead.

NumSweeps (Int) - number of sweeps for fine grid, up and down cycle.

Cycle1NumSweeps (Int) - number of sweeps for down cycle

Cycle2NumSweeps (Int) - number of sweeps for up cycle

Cycle3NumSweeps (Int) - number of sweeps for coarse grid

GridRelaxType (IntArray 1D) - type of smoother used on fine and coarse grid, up and down cycle. DEPRECATED: Use RelaxType or Cycle?RelaxType instead.

RelaxType (Int) - type of smoother for fine grid, up and down cycle.

Cycle1RelaxType (Int) - type of smoother for down cycle

Cycle2RelaxType (Int) - type of smoother for up cycle

Cycle3RelaxType (Int) - type of smoother for coarse grid

GridRelaxPoints (IntArray 2D) - point ordering used in relaxation. DEPRECATED.

RelaxWeight (DoubleArray 1D) - relaxation weight for smoothed Jacobi and hybrid SOR. DEPRE-CATED: Instead, use the RelaxWt parameter and the SetLevelRelaxWt function.

RelaxWt (Int) - relaxation weight for all levels for smoothed Jacobi and hybrid SOR.

TruncFactor (Double) - truncation factor for interpolation.

JacobiTruncThreshold (Double) - threshold for truncation of Jacobi interpolation.

SmoothType (Int) - more complex smoothers.

SmoothNumLevels (Int) - number of levels for more complex smoothers.

SmoothNumSweeps (Int) - number of sweeps for more complex smoothers.

PrintFileName (String) - name of file printed to in association with SetPrintLevel.

NumFunctions (Int) - size of the system of PDEs (when using the systems version).

DOFFunc (IntArray 1D) - mapping that assigns the function to each variable (when using the systems version).

Variant (Int) - variant of Schwarz used.

Overlap (Int) - overlap for Schwarz.

DomainType (Int) - type of domain used for Schwarz.

SchwarzRlxWeight (Double) - the smoothing parameter for additive Schwarz.

Tolerance (Double) - convergence tolerance, if this is used as a solver; ignored if this is used as a preconditioner

DebugFlag (Int) -

InterpType (Int) - Defines which parallel interpolation operator is used. There are the following options for interp_type:

0	classical modified interpolation
1	LS interpolation (for use with GSMG)
2	classical modified interpolation for hyperbolic PDEs
3	direct interpolation (with separation of weights)
4	multipass interpolation
5	multipass interpolation (with separation of weights)
6	extended classical modified interpolation
7	extended (if no common C neighbor) classical modified interpolation
8	standard interpolation
9	standard interpolation (with separation of weights)
10	classical block interpolation (for use with nodal systems version only)
11	classical block interpolation (for use with nodal systems version only)
	with diagonalized diagonal blocks
12	FF interpolation
13	FF1 interpolation

The default is 0.

NumSamples (Int) - Defines the number of sample vectors used in GSMG or LS interpolation.

MaxIterations (Int) - maximum number of iterations

Logging (Int) - Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply.

PrintLevel (Int) - Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply.

The following function is specific to this class:

SetLevelRelxWeight (Double , Int) - relaxation weight for one specified level of smoothed Jacobi and hybrid SOR.

Objects of this type can be cast to Solver objects using the __cast methods.

6.2.2

bHYPRE_BoomerAMG bHYPRE_BoomerAMG__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

__ 6.2.3 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_BoomerAMG_SetOperator (bHYPRE_BoomerAMG self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

_ 6.2.4 _____

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

6.2.5

SIDL_C_INLINE_DECL int32_t bHYPRE_BoomerAMG_SetMaxIterations (bHYPRE_BoomerAMG self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

6.2.6

SIDL_C_INLINE_DECL int32_t bHYPRE_BoomerAMG_SetLogging (bHYPRE_BoomerAMG self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

 $_$ 6.2.7 $_$

SIDL_C_INLINE_DECL int32_t bHYPRE_BoomerAMG_SetPrintLevel (bHYPRE_BoomerAMG self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

_ 6.2.8 _

SIDL_C_INLINE_DECL int32_t bHYPRE_BoomerAMG_SetCommunicator (bHYPRE_BoomerAMG self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

 $_$ 6.2.9 $_$

SIDL_C_INLINE_DECL void bHYPRE_BoomerAMG_Destroy (bHYPRE_BoomerAMG self, sidl_BaseInterface *_ex)

6.2.10

RMI connector function for the class. (no addref)

__ 6.3 _

ParCSR Euclid Solver

Names		
6.3.1	struct bHYPRE_Euclidobject Symbol "bHYPRE	149
	_ex Constructor function for the class	
	bHYPRE_Euclid bHYPRE_EuclidcreateRemote (const char * url, sidl_BaseInterface *_ex) RMI constructor function for the class	
	bHYPRE_Euclid bHYPRE_EuclidwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_Eucliddata) passed in rather than running the constructor	
6.3.2	bHYPRE_Euclid bHYPRE_Euclidconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	150
	bHYPRE_Euclid bHYPRE_MPICommunicator mpi_comm, bHYPRE_IJParCSRMatrix A, sidl_BaseInterface *_ex) This function is the preferred way to create a Euclid solver	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_Euclid_SetParameters (bHYPRE_Euclid self, int32_t argc, char** argv, sidl_BaseInterface *_ex)	
6.3.3	Method: SetParameters[] SIDL_C_INLINE_DECL_int32_t bHYPRE_Euclid_SetOperator (bHYPRE_Euclid self,	
	Set the operator for the linear system being solved	150
6.3.4	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_Euclid_SetTolerance (bHYPRE_Euclid self, double tolerance, sidl_BaseInterface *_ex)	
	(Optional) Set the convergence tolerance	150
6.3.5	SIDL_C_INLINE_DECL int32_t bHYPRE_Euclid_SetMaxIterations (bHYPRE_Euclid self,	
	sidl_BaseInterface *_ex)	150
	(Optional) Set maximum number of iterations	150
6.3.6	SIDL_C_INLINE_DECL int32_t bHYPRE_Euclid_SetLogging (bHYPRE_Euclid self, int32_t level,	
	(Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	151
6.3.7	SIDL_C_INLINE_DECL int32_t bHYPRE_Euclid_SetPrintLevel (bHYPRE_Euclid self, int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	151
	SIDL_C_INLINE_DECL int32_t bHYPRE_Euclid_GetNumIterations (bHYPRE_Euclid self,	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL int32_t bHYPRE_Euclid_GetRelResidualNorm (bHYPRE_Euclid self,	
	(Optional) Return the norm of the relative residual	
6.3.8	SIDL_C_INLINE_DECL int32_t bHYPRE_Euclid_SetCommunicator (bHYPRE_Euclid self,	
	Set the MPI Communicator	151
6.3.9	SIDL_C_INLINE_DECL void bHYPRE_Euclid_Destroy (bHYPRE_Euclid self, sidl_BaseInterface *_ex) The Destroy function doesn't necessarily destroy anything	151
	SIDL_C_INLINE_DECL int32_t bHYPRE_Euclid_SetIntParameter (bHYPRE_Euclid self,	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_Euclid_SetDoubleParameter (bHYPRE_Euclid self,	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_Euclid_SetStringParameter ( bHYPRE_Euclid self,
                                        const char* name, const char* value,
                                        sidl_BaseInterface *_ex)
      Set the string parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Euclid_SetIntArray1Parameter ( bHYPRE_Euclid self,
                                            const char* name,
                                            int32_t* value, int32_t nvalues,
                                            sidl_BaseInterface *_ex)
      Set the int 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Euclid_SetIntArray2Parameter ( bHYPRE_Euclid self,
                                            const char* name,
                                            struct sidl_int_array* value,
                                            sidl_BaseInterface *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Euclid_SetDoubleArray1Parameter ( bHYPRE_Euclid self,
                                                const char* name,
                                                double* value,
                                                int32_t nvalues,
                                                sidl_BaseInterface *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_Euclid_SetDoubleArray2Parameter ( bHYPRE_Euclid self,
                                                const char* name, struct
                                                sidl_double_array* value,
                                                sidl_BaseInterface *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Euclid_GetIntValue ( bHYPRE_Euclid self, const char* name,
                                int32_t* value, sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_Euclid_GetDoubleValue ( bHYPRE_Euclid self,
                                    const char* name, double* value,
                                    sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Euclid_Setup ( bHYPRE_Euclid self, bHYPRE_Vector b,
                         bHYPRE_Vector x, sidl_BaseInterface *_ex)
      (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_Euclid_Apply ( bHYPRE_Euclid self, bHYPRE_Vector b,
                          bHYPRE_Vector* x, sidl_BaseInterface *_ex)
```

Apply the operator to b, returning x

SIDL_C_INLINE_DECL int32_t

bHYPRE_Euclid_ApplyAdjoint (bHYPRE_Euclid self, bHYPRE_Vector b,

```
bHYPRE_Vector* x,
                                              sidl_BaseInterface *_ex)
                   Apply the adjoint of the operator to b, returning x
            _{\mathbf{ex}}
                   Cast method for interface and class type conversions
            void*
            bHYPRE_Euclid_cast2 (void* obj, const char* type, sidl_BaseInterface *_ex)
                   String cast method for interface and class type conversions
            SIDL_C_INLINE_DECL void
            bHYPRE_Euclid_exec ( bHYPRE_Euclid self, const char* methodName,
                                      sidl_rmi_Call inArgs, sidl_rmi_Return outArgs,
                                      sidl_BaseInterface *_ex)
                   Select and execute a method by name
            SIDL_C_INLINE_DECL char*
            bHYPRE_Euclid__getURL ( bHYPRE_Euclid self, sidl_BaseInterface *_ex)
                   Get the URL of the Implementation of this object (for RMI)
            SIDL_C_INLINE_DECL void
            bHYPRE_Euclid_raddRef ( bHYPRE_Euclid self, sidl_BaseInterface *_ex)
                   On a remote object, addrefs the remote instance
            SIDL_C_INLINE_DECL_sidl_bool
            bHYPRE_Euclid_isRemote ( bHYPRE_Euclid self, sidl_BaseInterface *_ex)
                   TRUE if this object is remote, false if local
            sidl_bool
            bHYPRE_Euclid__isLocal ( bHYPRE_Euclid self, sidl_BaseInterface *_ex)
                   TRUE if this object is remote, false if local
            **_ex
                   Cast method for interface and class type conversions
6.3.10
            **_ex
                   RMI connector function for the class .....
                                                                                              152
```

6.3.1

struct bHYPRE_Euclid_object

Symbol "bHYPRE.Euclid" (version 1.0.0)

Objects of this type can be cast to Solver objects using the __cast methods.

Although the usual Solver SetParameter functions are available, a Euclid-stype parameter-setting function is also available, SetParameters.

6.3.2

bHYPRE_Euclid bHYPRE_Euclid__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

___ 6.3.3 _____

Set the operator for the linear system being solved. DEPRECATED. use Create

__ 6.3.4 _____

SIDL_C_INLINE_DECL int32_t **bHYPRE_Euclid_SetTolerance** (bHYPRE_Euclid self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

6.3.5

SIDL_C_INLINE_DECL int32_t bHYPRE_Euclid_SetMaxIterations (bHYPRE_Euclid self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

6.3.6

SIDL_C_INLINE_DECL int32_t bHYPRE_Euclid_SetLogging (bHYPRE_Euclid self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

__ 6.3.7 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_Euclid_SetPrintLevel (bHYPRE_Euclid self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

__ 6.3.8 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_Euclid_SetCommunicator (bHYPRE_Euclid self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

_ 6.3.9 _

SIDL_C_INLINE_DECL void bHYPRE_Euclid_Destroy (bHYPRE_Euclid self, sidl_BaseInterface *_ex)

6.3.10

RMI connector function for the class. (no addref)

__ 6.4 _

ParCSR Schwarz Solver

\mathbf{Names}		
6.4.1	struct bHYPRE_Schwarzobject Symbol "bHYPRE	155
	_ex Constructor function for the class	
	bHYPRE_Schwarz bHYPRE_SchwarzcreateRemote (const char * url, sidl_BaseInterface *_ex) RMI constructor function for the class	
	bHYPRE_Schwarz bHYPRE_SchwarzwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_Schwarzdata) passed in rather than running the constructor	
6.4.2	bHYPRE_Schwarz bHYPRE_Schwarzconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	156
	bHYPRE_Schwarz bHYPRE_Schwarz_Create (bHYPRE_IJParCSRMatrix A, sidl_BaseInterface *_ex) This function is the preferred way to create a Schwarz solver	
6.4.3	SIDL_C_INLINE_DECL_int32_t bHYPRE_Schwarz_SetOperator (bHYPRE_Schwarz self,	15/
6.4.4	Set the operator for the linear system being solved	156
	(Optional) Set the convergence tolerance	156
6.4.5	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_Schwarz_SetMaxIterations (bHYPRE_Schwarz self,	
	int32_t max_iterations,	
	sidl_BaseInterface *_ex)	
	(Optional) Set maximum number of iterations	156
6.4.6	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_Schwarz_SetLogging (bHYPRE_Schwarz self, int32_t level,	
	sidl_BaseInterface *_ex)	
	(Optional) Set the logging level, specifying the degree of additional informa-	1 -
	tional data to be accumulated	157
6.4.7	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_Schwarz_SetPrintLevel (bHYPRE_Schwarz self, int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the print level, specifying the degree of informational data	
	to be printed either to the screen or to a file	157
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_Schwarz_GetNumIterations (bHYPRE_Schwarz self,	
	int32_t* num_iterations,	
	sidl_BaseInterface *_ex)	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_Schwarz_GetRelResidualNorm (bHYPRE_Schwarz self, double* norm,	
	sidl_BaseInterface *_ex)	
	(Optional) Return the norm of the relative residual	
6.4.8	SIDL_C_INLINE_DECL int32_t	
0.4.0	bHYPRE_Schwarz_SetCommunicator (bHYPRE_Schwarz self,	
	bHYPRE_MPICommunicator	
	mpi_comm, sidl_BaseInterface *_ex)	
	Set the MPI Communicator	157
6.4.9	SIDL_C_INLINE_DECL void	
	bHYPRE_Schwarz_Destroy (bHYPRE_Schwarz self,	
	sidl_BaseInterface *_ex)	1
	The Destroy function doesn't necessarily destroy anything	157
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_Schwarz_SetIntParameter (bHYPRE_Schwarz self,	
	const char* name, int32_t value, sidl_BaseInterface *_ex)	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_Schwarz_SetDoubleParameter (bHYPRE_Schwarz self,	
	const char* name, double value,	
	sidl_BaseInterface *_ex)	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_Schwarz_SetStringParameter ( bHYPRE_Schwarz self,
                                          const char* name,
                                         const char* value,
                                         sidl_BaseInterface *_ex)
      Set the string parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Schwarz_SetIntArray1Parameter ( bHYPRE_Schwarz self,
                                             const char* name,
                                             int32_t* value,
                                             int32_t nvalues.
                                             sidl_BaseInterface *_ex)
      Set the int 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Schwarz_SetIntArray2Parameter ( bHYPRE_Schwarz self,
                                             const char* name,
                                             struct sidl_int__array* value,
                                             sidl_BaseInterface *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Schwarz_SetDoubleArray1Parameter ( bHYPRE_Schwarz self,
                                                  const char* name,
                                                  double* value.
                                                  int32_t nvalues.
                                                  sidl_BaseInterface *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Schwarz_SetDoubleArray2Parameter ( bHYPRE_Schwarz self,
                                                  const char* name, struct
                                                  sidl_double_array* value,
                                                  sidl_BaseInterface *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Schwarz_GetIntValue ( bHYPRE_Schwarz self, const char* name,
                                  int32_t* value, sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_Schwarz_GetDoubleValue ( bHYPRE_Schwarz self,
                                      const char* name, double* value,
                                      sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Schwarz_Setup ( bHYPRE_Schwarz self, bHYPRE_Vector b,
                           bHYPRE_Vector x, sidl_BaseInterface *_ex)
      (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_Schwarz_Apply ( bHYPRE_Schwarz self, bHYPRE_Vector b,
                           bHYPRE_Vector* x, sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
```

```
bHYPRE_Schwarz_ApplyAdjoint (bHYPRE_Schwarz self,
                                                bHYPRE_Vector b, bHYPRE_Vector* x,
                                                sidl_BaseInterface *_ex)
                   Apply the adjoint of the operator to b, returning x
            _{\mathbf{ex}}
                   Cast method for interface and class type conversions
            void*
            bHYPRE_Schwarz_cast2 (void* obj, const char* type,
                                        sidl_BaseInterface *_ex)
                   String cast method for interface and class type conversions
            SIDL_C_INLINE_DECL void
            bHYPRE_Schwarz_exec ( bHYPRE_Schwarz self, const char* methodName,
                                       sidl_rmi_Call inArgs, sidl_rmi_Return outArgs,
                                       sidl_BaseInterface *_ex)
                   Select and execute a method by name
            SIDL_C_INLINE_DECL char*
            bHYPRE_Schwarz__getURL ( bHYPRE_Schwarz self,
                                           sidl_BaseInterface *_ex)
                   Get the URL of the Implementation of this object (for RMI)
            SIDL_C_INLINE_DECL void
            bHYPRE_Schwarz_raddRef ( bHYPRE_Schwarz self,
                                           sidl_BaseInterface *_ex)
                   On a remote object, addrefs the remote instance
            SIDL_C_INLINE_DECL sidl_bool
            bHYPRE_Schwarz__isRemote ( bHYPRE_Schwarz self,
                                            sidl_BaseInterface *_ex)
                   TRUE if this object is remote, false if local
            sidl_bool
            bHYPRE_Schwarz__isLocal ( bHYPRE_Schwarz self, sidl_BaseInterface *_ex)
                   TRUE if this object is remote, false if local
            **_ex
                   Cast method for interface and class type conversions
            **_ex
6.4.10
                   RMI connector function for the class ......
                                                                                             158
```

struct bHYPRE_Schwarz__object

Symbol "bHYPRE.Schwarz" (version 1.0.0)

Objects of this type can be cast to Solver objects using the __cast methods.

Schwarz requires an IJParCSR matrix

bHYPRE_Schwarz

bHYPRE_Schwarz__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

___ 6.4.3 _____

SIDL_C_INLINE_DECL int32_t

bHYPRE_Schwarz_SetOperator (bHYPRE_Schwarz self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

_ 6.4.4 _____

SIDL_C_INLINE_DECL int32_t

 $bHYPRE_Schwarz_SetTolerance \ (\ bHYPRE_Schwarz \ self, \ double \ tolerance, \\ sidl_BaseInterface *_ex)$

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

6.4.5

SIDL_C_INLINE_DECL int32_t

bHYPRE_Schwarz_SetMaxIterations (bHYPRE_Schwarz self, int32_t max_iterations, sidl_BaseInterface *_ex)

 $(Optional) \ Set \ maximum \ number \ of \ iterations. \ DEPRECATED \ use \ SetIntParameter$

SIDL_C_INLINE_DECL int32_t bHYPRE_Schwarz_SetLogging (bHYPRE_Schwarz self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

__ 6.4.7 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_Schwarz_SetPrintLevel (bHYPRE_Schwarz self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

__ 6.4.8 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_Schwarz_SetCommunicator (bHYPRE_Schwarz self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

 $_$ 6.4.9 $_$

SIDL_C_INLINE_DECL void bHYPRE_Schwarz_Destroy (bHYPRE_Schwarz self, sidl_BaseInterface *_ex)

RMI connector function for the class. (no addref)

__ 6.5 _

ParCSR ParaSails Solver

Names		
6.5.1	struct bHYPRE_ParaSails_object Symbol "bHYPRE	161
	_ex	
	Constructor function for the class	
	bHYPRE_ParaSails bHYPRE_ParaSailscreateRemote (const char * url,	
	· · · · · · · · · · · · · · · · · · ·	
	bHYPRE_ParaSails bHYPRE_ParaSailswrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_ParaSailsdata) passed in rather than running the constructor	
6.5.2	bHYPRE_ParaSails bHYPRE_ParaSailsconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	162
	bHYPRE_ParaSails bHYPRE_MPICommunicator mpi_comm, bHYPRE_IJParCSRMatrix A, sidl_BaseInterface *_ex) This function is the preferred way to create a ParaSails solver	
6.5.3	SIDL_C_INLINE_DECL_int32_t bHYPRE_ParaSails_SetOperator (bHYPRE_ParaSails self, bHYPRE_Operator A, sidl_BaseInterface *_ex)	169
	Set the operator for the linear system being solved	162
6.5.4	SIDL_C_INLINE_DECL int32_t bHYPRE_ParaSails_SetTolerance (bHYPRE_ParaSails self,	
	(Optional) Set the convergence tolerance	162
6.5.5	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_ParaSails_SetMaxIterations (bHYPRE_ParaSails self, int32_t max_iterations, sidl_BaseInterface *_ex)	
	(Optional) Set maximum number of iterations	162
6.5.6	SIDL_C_INLINE_DECL int32_t bHYPRE_ParaSails_SetLogging (bHYPRE_ParaSails self, int32_t level, sidl_BaseInterface *_ex) (Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	163
6.5.7	SIDL_C_INLINE_DECL_int32_t bHYPRE_ParaSails_SetPrintLevel (bHYPRE_ParaSails self, int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	163
	SIDL_C_INLINE_DECL int32_t bHYPRE_ParaSails_GetNumIterations (bHYPRE_ParaSails self,	
	SIDL_C_INLINE_DECL int32_t bHYPRE_ParaSails_GetRelResidualNorm (bHYPRE_ParaSails self, double* norm, sidl_BaseInterface *_ex)	
	(Optional) Return the norm of the relative residual	
6.5.8	SIDL_C_INLINE_DECL int32_t bHYPRE_ParaSails_SetCommunicator (bHYPRE_ParaSails self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)	
	Set the MPI Communicator	163
6.5.9	SIDL_C_INLINE_DECL void bHYPRE_ParaSails self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	164
	SIDL_C_INLINE_DECL int32_t bHYPRE_ParaSails_SetIntParameter (bHYPRE_ParaSails self,	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_ParaSails_SetDoubleParameter (bHYPRE_ParaSails self,	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_ParaSails_SetStringParameter ( bHYPRE_ParaSails self,
                                           const char* name,
                                           const char* value,
                                           sidl_BaseInterface *_ex)
       Set the string parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_ParaSails_SetIntArray1Parameter ( bHYPRE_ParaSails self,
                                               const char* name,
                                               int32_t* value,
                                               int32_t nvalues.
                                               sidl_BaseInterface *_ex)
      Set the int 1-D array parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_ParaSails_SetIntArray2Parameter ( bHYPRE_ParaSails self,
                                               const char* name,
                                               struct sidl_int_array* value,
                                               sidl_BaseInterface *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_ParaSails_SetDoubleArray1Parameter ( bHYPRE_ParaSails self,
                                                    const char* name,
                                                    double* value.
                                                    int32_t nvalues,
                                                    sidl_BaseInterface *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_ParaSails_SetDoubleArray2Parameter ( bHYPRE_ParaSails self,
                                                    const char* name,
                                                    struct sidl_double_arrav*
                                                    value.
                                                    sidl_BaseInterface *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_ParaSails_GetIntValue ( bHYPRE_ParaSails self,
                                   const char* name, int32_t* value,
                                   sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_ParaSails_GetDoubleValue ( bHYPRE_ParaSails self,
                                        const char* name, double* value,
                                        sidl_BaseInterface *_ex)
       Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_ParaSails_Setup ( bHYPRE_ParaSails self, bHYPRE_Vector b,
                            bHYPRE_Vector x, sidl_BaseInterface *_ex)
       (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
```

```
bHYPRE_ParaSails_Apply ( bHYPRE_ParaSails self, bHYPRE_Vector b,
                             bHYPRE_Vector* x, sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_ParaSails_ApplyAdjoint ( bHYPRE_ParaSails self,
                                     bHYPRE_Vector b,
                                     bHYPRE_Vector* x,
                                     sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_ex
       Cast method for interface and class type conversions
void*
bHYPRE_ParaSails_cast2 (void* obj, const char* type,
                             sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
bHYPRE_ParaSails__exec ( bHYPRE_ParaSails self,
                            const char* methodName, sidl_rmi_Call inArgs,
                            sidl_rmi_Return outArgs, sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL_char*
bHYPRE_ParaSails__getURL ( bHYPRE_ParaSails self,
                                sidl_BaseInterface *_ex)
       Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL void
bHYPRE_ParaSails__raddRef ( bHYPRE_ParaSails self,
                                sidl_BaseInterface *_ex)
       On a remote object, addrefs the remote instance
SIDL_C_INLINE_DECL_sidl_bool
bHYPRE_ParaSails__isRemote ( bHYPRE_ParaSails self,
                                 sidl_BaseInterface *_ex)
       TRUE if this object is remote, false if local
sidl_bool
bHYPRE_ParaSails__isLocal ( bHYPRE_ParaSails self,
                               sidl_BaseInterface *_ex)
       TRUE if this object is remote, false if local
**_ex
       Cast method for interface and class type conversions
\mathbf{**}_{-}\mathbf{ex}
       RMI connector function for the class .....
                                                                                  164
```

6.5.1

6.5.10

struct bHYPRE_ParaSails_object

Symbol "bHYPRE.ParaSails" (version 1.0.0)

Objects of this type can be cast to Solver objects using the __cast methods.

ParaSails requires an IJParCSR matrix

 $_{-}$ 6.5.2 $_{-}$

bHYPRE_ParaSails
bHYPRE_ParaSails__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

6.5.3

SIDL_C_INLINE_DECL int32_t bHYPRE_ParaSails_SetOperator (bHYPRE_ParaSails self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

 $_$ 6.5.4 $_$

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

 $_$ 6.5.5 $_$

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

6.5.6

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

6.5.7

SIDL_C_INLINE_DECL int32_t bHYPRE_ParaSails_SetPrintLevel (bHYPRE_ParaSails self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

6.5.8

SIDL_C_INLINE_DECL int32_t
bHYPRE_ParaSails_SetCommunicator (bHYPRE_ParaSails self,
bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

6.5.9

SIDL_C_INLINE_DECL_ void

bHYPRE_ParaSails_Destroy (bHYPRE_ParaSails self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

6.5.10

RMI connector function for the class. (no addref)

6.6

ParCSR Pilut Solver

Names 6.6.1	struct bHYPRE_Pilut_object	
	$Symbol\ "bHYPRE$	167
	_ex	
	Constructor function for the class	
	bHYPRE_Pilut	
	bHYPRE_PilutcreateRemote (const char * url, sidl_BaseInterface *_ex) RMI constructor function for the class	
	bHYPRE_Pilut	
	bHYPRE_PilutwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_Pilut_data) passed in rather than running the constructor	
6.6.2	bHYPRE_Pilut	
	bHYPRE_Pilutconnect (const char *, sidl_BaseInterface *_ex)	
	RMI connector function for the class	168
	bHYPRE_Pilut	
	bHYPRE_Pilut_Create (bHYPRE_MPICommunicator mpi_comm,	
	bHYPRE_Operator A, sidl_BaseInterface *_ex)	
	This function is the preferred way to create a Pilut solver	
6.6.3	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_Pilut_SetOperator (bHYPRE_Pilut self, bHYPRE_Operator A, sidl_BaseInterface *_ex) Set the operator for the linear system being solved	168
e e 4		100
6.6.4	SIDL_C_INLINE_DECL int32_t bHYPRE_Pilut_SetTolerance (bHYPRE_Pilut self, double tolerance,	168
6.6.5	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_Pilut_SetMaxIterations (bHYPRE_Pilut self, int32_t max_iterations, sidl_BaseInterface *_ex)	
	(Optional) Set maximum number of iterations	168
6.6.6	SIDL_C_INLINE_DECL int32_t bHYPRE_Pilut_SetLogging (bHYPRE_Pilut self, int32_t level,	
	(Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	169
6.6.7	SIDL_C_INLINE_DECL int32_t bHYPRE_Pilut_SetPrintLevel (bHYPRE_Pilut self, int32_t level,	
	sidl_BaseInterface *_ex) (Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	169
	SIDL_C_INLINE_DECL int32_t bHYPRE_Pilut_GetNumIterations (bHYPRE_Pilut self,	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL int32_t bHYPRE_Pilut_GetRelResidualNorm (bHYPRE_Pilut self, double* norm,	
	(Optional) Return the norm of the relative residual	
6.6.8	SIDL_C_INLINE_DECL int32_t bHYPRE_Pilut_SetCommunicator (bHYPRE_Pilut self,	
	Set the MPI Communicator	169
6.6.9	SIDL_C_INLINE_DECL void bHYPRE_Pilut_Destroy (bHYPRE_Pilut self, sidl_BaseInterface *_ex) The Destroy function doesn't necessarily destroy anything	169
	SIDL_C_INLINE_DECL int32_t bHYPRE_Pilut_SetIntParameter (bHYPRE_Pilut self, const char* name, int32_t value, sidl_BaseInterface *_ex)	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_Pilut_SetDoubleParameter (bHYPRE_Pilut self,	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_Pilut_SetStringParameter ( bHYPRE_Pilut self,
                                       const char* name, const char* value,
                                       sidl_BaseInterface *_ex)
      Set the string parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Pilut_SetIntArray1Parameter ( bHYPRE_Pilut self,
                                           const char* name, int32_t* value,
                                           int32_t nvalues,
                                          sidl_BaseInterface *_ex)
      Set the int 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Pilut_SetIntArray2Parameter ( bHYPRE_Pilut self,
                                          const char* name,
                                          struct sidl_int_array* value,
                                          sidl_BaseInterface *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Pilut_SetDoubleArray1Parameter ( bHYPRE_Pilut self,
                                               const char* name,
                                               double* value,
                                               int32_t nvalues,
                                               sidl_BaseInterface *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_Pilut_SetDoubleArray2Parameter ( bHYPRE_Pilut self,
                                               const char* name, struct
                                               sidl_double_array* value,
                                               sidl_BaseInterface *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Pilut_GetIntValue ( bHYPRE_Pilut self, const char* name,
                               int32_t* value, sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL_int32_t
bHYPRE_Pilut_GetDoubleValue ( bHYPRE_Pilut self, const char* name,
                                   double* value, sidl_BaseInterface *_ex)
       Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_Pilut_Setup ( bHYPRE_Pilut self, bHYPRE_Vector b,
                        bHYPRE_Vector x, sidl_BaseInterface *_ex)
       (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_Pilut_Apply ( bHYPRE_Pilut self, bHYPRE_Vector b,
                        bHYPRE_Vector* x, sidl_BaseInterface *_ex)
       Apply the operator to b, returning x
```

SIDL C INLINE DECL int32 t

```
bHYPRE_Pilut_ApplyAdjoint ( bHYPRE_Pilut self, bHYPRE_Vector b,
                                bHYPRE_Vector* x, sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_{\mathbf{ex}}
       Cast method for interface and class type conversions
void*
bHYPRE_Pilut__cast2 (void* obj, const char* type, sidl_BaseInterface *_ex)
       String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
bHYPRE_Pilut_exec ( bHYPRE_Pilut self, const char* methodName,
                       sidl_rmi_Call inArgs, sidl_rmi_Return outArgs,
                       sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL_char*
bHYPRE_Pilut__getURL ( bHYPRE_Pilut self, sidl_BaseInterface *_ex)
       Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL void
bHYPRE_Pilut_raddRef ( bHYPRE_Pilut self, sidl_BaseInterface *_ex)
       On a remote object, addrefs the remote instance
SIDL_C_INLINE_DECL_sidl_bool
bHYPRE_Pilut__isRemote ( bHYPRE_Pilut self, sidl_BaseInterface *_ex)
       TRUE if this object is remote, false if local
sidl_bool
bHYPRE_Pilut__isLocal ( bHYPRE_Pilut self, sidl_BaseInterface *_ex)
       TRUE if this object is remote, false if local
**_ex
       Cast method for interface and class type conversions
**_ex
       RMI connector function for the class .....
                                                                                 170
```

6.6.1

6.6.10

struct bHYPRE_Pilut_object

Symbol "bHYPRE.Pilut" (version 1.0.0)

Objects of this type can be cast to Solver objects using the __cast methods.

Pilut has not been implemented yet.

6.6.2

bHYPRE_Pilut bHYPRE_Pilut__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

____ 6.6.3 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_Pilut_SetOperator (bHYPRE_Pilut self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

664

SIDL_C_INLINE_DECL int32_t **bHYPRE_Pilut_SetTolerance** (bHYPRE_Pilut self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

___ 6.6.5 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_Pilut_SetMaxIterations (bHYPRE_Pilut_self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

6.6.6

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

__ 6.6.7 _____

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

__ 6.6.8 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_Pilut_SetCommunicator (bHYPRE_Pilut_self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

_ 6.6.9 _

SIDL_C_INLINE_DECL void bHYPRE_Pilut_Destroy (bHYPRE_Pilut self, sidl_BaseInterface *_ex)

6610

RMI connector function for the class. (no addref)

. 7

Structured Matrix Solvers

Names		
7.1	StructDiagScale Solver	
		171
7.2	Struct Jacobi Solver	
		178
7.3	Struct PFMG Solver	
		184
7.4	Struct SMG Solver	
		191

These solvers use structured matrix/vector storage schemes.

_ 7.1 _

${\bf Struct Diag Scale\ Solver}$

Names		
7.1.1	struct bHYPRE_StructDiagScaleobject Symbol "bHYPRE	175
	_ex Constructor function for the class	
	bHYPRE_StructDiagScale bHYPRE_StructDiagScalecreateRemote (const char * url,	
	bHYPRE_StructDiagScale bHYPRE_StructDiagScalewrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_StructDiagScaledata) passed in rather than running the constructor	
7.1.2	bHYPRE_StructDiagScale bHYPRE_StructDiagScaleconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	176
	bHYPRE_StructDiagScale	

	bHYPRE_StructDiagScale_Create (bHYPRE_MPICommunicator mpi_comm, bHYPRE_StructMatrix A, sidl_BaseInterface *_ex)	
	This function is the preferred way to create a Struct DiagScale solver	
7.1.3	SIDL_C_INLINE_DECL int32_t bHYPRE_StructDiagScale_SetOperator (bHYPRE_StructDiagScale self, bHYPRE_Operator A, sidl_BaseInterface *_ex)	
	Set the operator for the linear system being solved	176
7.1.4	SIDL_C_INLINE_DECL_int32_t bHYPRE_StructDiagScale_SetTolerance (bHYPRE_StructDiagScale self, double tolerance, sidl_BaseInterface *_ex)	
	(Optional) Set the convergence tolerance	176
7.1.5	SIDL_C_INLINE_DECL int32_t bHYPRE_StructDiagScale_SetMaxIterations (bHYPRE_StructDiagScale self, int32_t max_iterations, sidl_BaseInterface *_ex)	
	(Optional) Set maximum number of iterations	176
7.1.6	SIDL_C_INLINE_DECL int32_t bHYPRE_StructDiagScale_SetLogging (bHYPRE_StructDiagScale self,	177
7.1.7	SIDL_C_INLINE_DECL_int32_t bHYPRE_StructDiagScale_SetPrintLevel (bHYPRE_StructDiagScale self, int32_t level, sidl_BaseInterface *_ex) (Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	177
	SIDL_C_INLINE_DECL int32_t bHYPRE_StructDiagScale_GetNumIterations (bHYPRE_StructDiagScale self, int32_t* num_iterations,	111
	sidl_BaseInterface *_ex) (Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_StructDiagScale_GetRelResidualNorm (bHYPRE_StructDiagScale self, double* norm, sidl_BaseInterface *_ex)	
	(Optional) Return the norm of the relative residual	
7.1.8	SIDL_C_INLINE_DECL int32_t	

	$b HYPRE_StructDiagScale_SetCommunicator \left(\begin{array}{c} b HYPRE_StructDiagScale \\ \end{array} \right.$	
	self,	
	bHYPRE_MPICommunicator	
	mpi_comm, sidl_BaseInterface *_ex)	
	Set the MPI Communicator	177
7.1.9	SIDL_C_INLINE_DECL void	
1.1.9	bHYPRE_StructDiagScale_Destroy (bHYPRE_StructDiagScale self,	
	sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	177
	SIDL_C_INLINE_DECL int32_t	
	$\mathbf{bHYPRE_StructDiagScale_SetIntParameter} \ (\ \ \mathbf{bHYPRE_StructDiagScale}$	
	self, const char* name,	
	int32_t value,	
	sidl_BaseInterface *_ex)	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_StructDiagScale_SetDoubleParameter (
	bHYPRE_StructDiagScale self, const char* name,	
	double value,	
	sidl_BaseInterface *_ex)	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	
	${\bf bHYPRE_StructDiagScale_SetStringParameter} \ ($	
	$b HYPRE_StructDiagScale$	
	self, const char* name,	
	const char* value,	
	sidl_BaseInterface *_ex) Set the string parameter associated with name	
	· -	
	SIDL_C_INLINE_DECL int32_t bHYPRE_StructDiagScale_SetIntArray1Parameter (
	bHYPRE_StructDiagScale_SetIntArray11 arameter (bHYPRE_StructDiagScale	
	self,	
	const char* name,	
	$int32_{-}t^*$ value,	
	int32 ₋ t nvalues,	
	$\operatorname{sidl_BaseInterface}^{\star}$	
	*_ex) Set the int 1-D array parameter associated with name	
	· -	
	SIDL_C_INLINE_DECL int32_t bHVDDE Struct DiogScale Set Int A prov2Department (
	$b HYPRE_StructDiagScale_SetIntArray2Parameter (\\bHYPRE_StructDiagScale$	
	self,	
	const char* name,	
	struct sidl_int_array*	
	value,	
	$\operatorname{sidl_BaseInterface}$	
	*_ex)	
	Set the int 2-D array parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_StructDiagScale_SetDoubleArray1Parameter (
                                                           bHYPRE_StructDiagScale
                                                           self, const char*
                                                           name,
                                                           double* value,
                                                           int32_t nvalues,
                                                           sidl_BaseInterface
                                                           *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructDiagScale_SetDoubleArray2Parameter (
                                                           b HYPRE\_StructDiagScale
                                                           self, const char*
                                                           name, struct
                                                           sidl_double_array*
                                                           value,
                                                           sidl_BaseInterface
                                                           *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructDiagScale_GetIntValue ( bHYPRE_StructDiagScale self,
                                          const char* name, int32_t* value,
                                          sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE\_StructDiagScale\_GetDoubleValue ( bHYPRE\_StructDiagScale
                                               self, const char* name,
                                               double* value.
                                               sidl_BaseInterface *_ex)
       Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructDiagScale_Setup ( bHYPRE_StructDiagScale self,
                                    bHYPRE_Vector b, bHYPRE_Vector x,
                                    sidl_BaseInterface *_ex)
       (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL_int32_t
bHYPRE_StructDiagScale_Apply ( bHYPRE_StructDiagScale self,
                                    bHYPRE_Vector b, bHYPRE_Vector* x,
                                    sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructDiagScale_ApplyAdjoint ( bHYPRE_StructDiagScale self,
                                            bHYPRE_Vector b,
                                            bHYPRE_Vector* x,
                                            sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_{\mathbf{ex}}
       Cast method for interface and class type conversions
void*
```

bHYPRE_StructDiagScale__cast2 (void* obj, const char* type, sidl_BaseInterface *_ex) String cast method for interface and class type conversions SIDL_C_INLINE_DECL_void bHYPRE_StructDiagScale_exec (bHYPRE_StructDiagScale self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex) Select and execute a method by name SIDL_C_INLINE_DECL char* bHYPRE_StructDiagScale__getURL (bHYPRE_StructDiagScale self, sidl_BaseInterface *_ex) Get the URL of the Implementation of this object (for RMI) SIDL_C_INLINE_DECL void bHYPRE_StructDiagScale_raddRef (bHYPRE_StructDiagScale self, sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance SIDL_C_INLINE_DECL sidl_bool bHYPRE_StructDiagScale__isRemote (bHYPRE_StructDiagScale self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local $sidl_bool$ bHYPRE_StructDiagScale__isLocal (bHYPRE_StructDiagScale self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local **_ex

7.1.10 ******_**ex**

RMI connector function for the class

Cast method for interface and class type conversions

7.1.1

struct bHYPRE_StructDiagScale_object

Symbol "bHYPRE.StructDiagScale" (version 1.0.0)

Diagonal scaling preconditioner for STruct matrix class.

Objects of this type can be cast to Solver objects using the __cast methods.

178

7.1.2

bHYPRE_StructDiagScale
bHYPRE_StructDiagScale__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

__ 7.1.3 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_StructDiagScale_SetOperator (bHYPRE_StructDiagScale self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

7.1.4

SIDL_C_INLINE_DECL int32_t bHYPRE_StructDiagScale_SetTolerance (bHYPRE_StructDiagScale self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

7.1.5

SIDL_C_INLINE_DECL int32_t bHYPRE_StructDiagScale_SetMaxIterations (bHYPRE_StructDiagScale self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

7.1.6

SIDL_C_INLINE_DECL int32_t bHYPRE_StructDiagScale_SetLogging (bHYPRE_StructDiagScale self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

$_$ 7.1.7 $_-$

SIDL_C_INLINE_DECL int32_t bHYPRE_StructDiagScale_SetPrintLevel (bHYPRE_StructDiagScale self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

_ 7.1.8 _

SIDL_C_INLINE_DECL int32_t bHYPRE_StructDiagScale_SetCommunicator (bHYPRE_StructDiagScale self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

$_{-}$ 7.1.9 $_{-}$

SIDL_C_INLINE_DECL_void bHYPRE_StructDiagScale_Destroy (bHYPRE_StructDiagScale self, sidl_BaseInterface *_ex)

7.1.10

struct bHYPRE_StructDiagScale__object* bHYPRE_StructDiagScale__connectI const char * url sidl_bool ar struct sidl_BaseInterface__object **_ex

RMI connector function for the class. (no addref)

_ 7.2 _

Struct Jacobi Solver

Names		
7.2.1	struct bHYPRE_StructJacobiobject Symbol "bHYPRE	182
	_ex Constructor function for the class	
	bHYPRE_StructJacobi bHYPRE_StructJacobicreateRemote (const char * url,	
	bHYPRE_StructJacobi bHYPRE_StructJacobiwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_StructJacobidata) passed in rather than running the con- structor	
7.2.2	bHYPRE_StructJacobi bHYPRE_StructJacobiconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	182
	bHYPRE_StructJacobi bHYPRE_MPICommunicator mpi_comm, bHYPRE_StructMatrix A, sidl_BaseInterface *_ex)	
	This function is the preferred way to create a Struct Jacobi solver	
7.2.3	SIDL_C_INLINE_DECL_int32_t bHYPRE_StructJacobi_SetOperator (bHYPRE_StructJacobi self, bHYPRE_Operator A, sidl_BaseInterface *_ex)	
	Set the operator for the linear system being solved	182
7.2.4	SIDL_C_INLINE_DECL_int32_t	

	bHYPRE_StructJacobi_SetTolerance (bHYPRE_StructJacobi self,	
	double tolerance,	
	sidl_BaseInterface *_ex)	
	(Optional) Set the convergence tolerance	183
7.2.5	SIDL_C_INLINE_DECL int32_t	
	$\mathbf{bHYPRE_StructJacobi_SetMaxIterations} \ (\ \ \mathbf{bHYPRE_StructJacobi} \ \mathbf{self},$	
	int32_t max_iterations,	
	sidl_BaseInterface *_ex)	400
	(Optional) Set maximum number of iterations	183
7.2.6	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_StructJacobi_SetLogging (bHYPRE_StructJacobi self,	
	int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	183
7.2.7	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_StructJacobi_SetPrintLevel (bHYPRE_StructJacobi self,	
	int32_t level,	
	sidl_BaseInterface *_ex)	
	(Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	183
	SIDL_C_INLINE_DECL int32_t	
	$\mathbf{bHYPRE_StructJacobi_GetNumIterations} \ (\ \ \mathbf{bHYPRE_StructJacobi\ self},$	
	int32_t* num_iterations,	
	sidl_BaseInterface *_ex)	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_StructJacobi_GetRelResidualNorm (bHYPRE_StructJacobi self,	
	double* norm,	
	sidl_BaseInterface *_ex) (Optional) Return the norm of the relative residual	
	· -	
7.2.8	SIDL_C_INLINE_DECL int32_t bHYPRE_StructJacobi_SetCommunicator (bHYPRE_StructJacobi self,	
	bHYPRE_MPICommunicator	
	mpi_comm,	
	sidl_BaseInterface *_ex)	
	Set the MPI Communicator	184
7.2.9	SIDL_C_INLINE_DECL_void	
	bHYPRE_StructJacobi_Destroy (bHYPRE_StructJacobi self,	
	sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	184
	SIDL_C_INLINE_DECL int32_t	
	$\mathbf{bHYPRE_StructJacobi_SetIntParameter} \ (\ \mathbf{bHYPRE_StructJacobi\ self},$	
	const char* name, int32_t value,	
	sidl_BaseInterface *_ex)	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL_int32_t	

```
bHYPRE_StructJacobi_SetDoubleParameter ( bHYPRE_StructJacobi self,
                                                const char* name,
                                                double value,
                                                sidl_BaseInterface *_ex)
      Set the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructJacobi_SetStringParameter ( bHYPRE_StructJacobi self,
                                               const char* name,
                                               const char* value,
                                               sidl_BaseInterface *_ex)
      Set the string parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructJacobi_SetIntArray1Parameter ( bHYPRE_StructJacobi
                                                   self, const char* name,
                                                   int32_t* value,
                                                   int32_t nvalues.
                                                   sidl_BaseInterface *_ex)
      Set the int 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructJacobi_SetIntArray2Parameter ( bHYPRE_StructJacobi
                                                   self, const char* name,
                                                   struct sidl_int_array*
                                                   value.
                                                   sidl_BaseInterface *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructJacobi_SetDoubleArray1Parameter (
                                                       bHYPRE_StructJacobi
                                                       self.
                                                       const char* name,
                                                       double* value,
                                                       int32_t nvalues,
                                                       sidl\_BaseInterface
                                                       *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructJacobi_SetDoubleArray2Parameter (
                                                       bHYPRE\_StructJacobi
                                                       const char* name,
                                                       struct
                                                       sidl_double_array*
                                                       value.
                                                       sidl_BaseInterface
                                                       *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
```

```
bHYPRE_StructJacobi_GetIntValue ( bHYPRE_StructJacobi self.
                                       const char* name, int32_t* value,
                                       sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructJacobi_GetDoubleValue ( bHYPRE_StructJacobi self,
                                           const char* name, double* value,
                                           sidl_BaseInterface *_ex)
       Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructJacobi_Setup ( bHYPRE_StructJacobi self,
                                bHYPRE_Vector b, bHYPRE_Vector x,
                                sidl_BaseInterface *_ex)
       (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructJacobi_Apply ( bHYPRE_StructJacobi self,
                                bHYPRE_Vector b, bHYPRE_Vector* x,
                                sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL_int32_t
bHYPRE_StructJacobi_ApplyAdjoint ( bHYPRE_StructJacobi self,
                                        bHYPRE_Vector b.
                                        bHYPRE_Vector* x,
                                        sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_ex
       Cast method for interface and class type conversions
void*
bHYPRE_StructJacobi_cast2 (void* obj, const char* type,
                                sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
bHYPRE_StructJacobi_exec ( bHYPRE_StructJacobi self,
                               const char* methodName,
                               sidl_rmi_Call inArgs, sidl_rmi_Return outArgs,
                               sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL char*
bHYPRE_StructJacobi__getURL ( bHYPRE_StructJacobi self,
                                   sidl_BaseInterface *_ex)
       Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL void
bHYPRE_StructJacobi_raddRef ( bHYPRE_StructJacobi self,
                                   sidl_BaseInterface *_ex)
       On a remote object, addrefs the remote instance
```

SIDL_C_INLINE_DECL_sidl_bool

bHYPRE_StructJacobi__isRemote (bHYPRE_StructJacobi self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

sidl_bool

bHYPRE_StructJacobi__isLocal (bHYPRE_StructJacobi self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

**_ex

Cast method for interface and class type conversions

RMI connector function for the class

7.2.1

**_ex

7.2.10

struct bHYPRE_StructJacobi_object

Symbol "bHYPRE.StructJacobi" (version 1.0.0)

Objects of this type can be cast to Solver objects using the __cast methods.

The StructJacobi solver requires a Struct matrix.

7.2.2

RMI connector function for the class.(addrefs)

7.2.3

SIDL_C_INLINE_DECL int32_t bHYPRE_StructJacobi_SetOperator (bHYPRE_StructJacobi self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

184

7.2.4

SIDL_C_INLINE_DECL int32_t bHYPRE_StructJacobi_SetTolerance (bHYPRE_StructJacobi self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

__ 7.2.5 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_StructJacobi_SetMaxIterations (bHYPRE_StructJacobi self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

 $_{-}$ 7.2.6 $_{--}$

SIDL_C_INLINE_DECL int32_t bHYPRE_StructJacobi_SetLogging (bHYPRE_StructJacobi self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the $logging\ level$, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

7.2.7

SIDL_C_INLINE_DECL int32_t bHYPRE_StructJacobi_SetPrintLevel (bHYPRE_StructJacobi self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

7.2.8

SIDL_C_INLINE_DECL int32_t bHYPRE_StructJacobi_SetCommunicator (bHYPRE_StructJacobi self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

_ 7.2.9 _

SIDL_C_INLINE_DECL void **bHYPRE_StructJacobi_Destroy** (bHYPRE_StructJacobi self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

_ 7.2.10 _

RMI connector function for the class. (no addref)

7.3

Struct PFMG Solver

Names

7.3.1 struct bHYPRE_StructPFMG__object

Symbol "bHYPRE

188

 $_{\mathbf{ex}}$

Constructor function for the class

bHYPRE_StructPFMG

	bHYPRE_StructPFMGcreateRemote (const char * url,	
	sidl_BaseInterface *_ex)	
	RMI constructor function for the class	
	bHYPRE_StructPFMG bHYPRE_StructPFMGwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_StructPFMGdata) passed in rather than running the con- structor	
7.3.2	bHYPRE_StructPFMG bHYPRE_StructPFMGconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	189
	bHYPRE_StructPFMG bHYPRE_MPICommunicator mpi_comm, bHYPRE_StructMatrix A, sidl_BaseInterface *_ex)	
	This function is the preferred way to create a Struct PFMG solver	
7.3.3	SIDL_C_INLINE_DECL int32_t bHYPRE_StructPFMG_SetOperator (bHYPRE_StructPFMG self,	
	Set the operator for the linear system being solved	189
7.3.4	SIDL_C_INLINE_DECL int32_t bHYPRE_StructPFMG_SetTolerance (bHYPRE_StructPFMG self,	
	(Optional) Set the convergence tolerance	189
7.3.5	SIDL_C_INLINE_DECL int32_t bHYPRE_StructPFMG_SetMaxIterations (bHYPRE_StructPFMG self, int32_t max_iterations, sidl_BaseInterface *_ex) (Optional) Set maximum number of iterations	189
7.3.6	SIDL_C_INLINE_DECL int32_t bHYPRE_StructPFMG_SetLogging (bHYPRE_StructPFMG self,	190
7.3.7	SIDL_C_INLINE_DECL int32_t bHYPRE_StructPFMG_SetPrintLevel (bHYPRE_StructPFMG self,	
	to be printed either to the screen or to a file	190
	SIDL_C_INLINE_DECL int32_t bHYPRE_StructPFMG_GetNumIterations (bHYPRE_StructPFMG self, int32_t* num_iterations, sidl_BaseInterface *_ex)	
	(Optional) Return the number of iterations taken	
	SIDL C_INLINE_DECL_int32_t	

	bHYPRE_StructPFMG_GetRelResidualNorm (bHYPRE_StructPFMG	
	self, double* norm, sidl_BaseInterface *_ex)	
	(Optional) Return the norm of the relative residual	
	· - /	
7.3.8	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_StructPFMG_SetCommunicator (bHYPRE_StructPFMG self, bHYPRE_MPICommunicator	
	mpi_comm,	
	sidl_BaseInterface *_ex)	
	Set the MPI Communicator	190
7.3.9	SIDL_C_INLINE_DECL_void	
.0.0	bHYPRE_StructPFMG_Destroy (bHYPRE_StructPFMG self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	190
		150
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_StructPFMG_SetIntParameter (bHYPRE_StructPFMG self, const char* name, int32_t value,	
	sidl_BaseInterface *_ex)	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_StructPFMG_SetDoubleParameter (bHYPRE_StructPFMG	
	self, const char* name,	
	double value,	
	sidl_BaseInterface *_ex)	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_StructPFMG_SetStringParameter (bHYPRE_StructPFMG self,	
	const char* name,	
	const char* value, sidl_BaseInterface *_ex)	
	Set the string parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_StructPFMG_SetIntArray1Parameter (bHYPRE_StructPFMG	
	self, const char* name,	
	$int32_{-}t^*$ value,	
	$int32_{-}t$ nvalues,	
	sidl_BaseInterface *_ex)	
	Set the int 1-D array parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	
	$b HYPRE_StructPFMG_SetIntArray2Parameter \left(\begin{array}{c} bHYPRE_StructPFMG \end{array} \right.$	
	self, const char* name,	
	struct sidl_intarray*	
	value, sidl_BaseInterface *_ex)	
	Set the int 2-D array parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	
	DIDD_O_INDINE_DEOD III032_0	

bHYPRE_StructPFMG_SetDoubleArray1Parameter (

```
bHYPRE_StructPFMG
                                                      const char* name,
                                                      double* value,
                                                      int32_t nvalues,
                                                      sidl_BaseInterface
                                                      *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructPFMG_SetDoubleArray2Parameter (
                                                      bHYPRE_StructPFMG
                                                      self,
                                                      const char* name,
                                                      struct
                                                      sidl_double_array*
                                                      value,
                                                      sidl_BaseInterface
                                                      *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructPFMG_GetIntValue ( bHYPRE_StructPFMG self,
                                      const char* name, int32_t* value,
                                       sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructPFMG_GetDoubleValue ( bHYPRE_StructPFMG self,
                                           const char* name.
                                           double* value,
                                           sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructPFMG_Setup ( bHYPRE_StructPFMG self,
                                bHYPRE_Vector b, bHYPRE_Vector x,
                                sidl_BaseInterface *_ex)
      (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructPFMG_Apply ( bHYPRE_StructPFMG self,
                                bHYPRE_Vector b, bHYPRE_Vector* x,
                                sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructPFMG_ApplyAdjoint ( bHYPRE_StructPFMG self,
                                        bHYPRE_Vector b,
                                        bHYPRE_Vector* x,
                                        sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
```

_ex

Cast method for interface and class type conversions

void*

bHYPRE_StructPFMG__cast2 (void* obj, const char* type, sidl_BaseInterface *_ex)

String cast method for interface and class type conversions

SIDL_C_INLINE_DECL void

bHYPRE_StructPFMG__exec (bHYPRE_StructPFMG self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs,

Select and execute a method by name

SIDL_C_INLINE_DECL char*

bHYPRE_StructPFMG__getURL (bHYPRE_StructPFMG self, sidl_BaseInterface *_ex)

Get the URL of the Implementation of this object (for RMI)

sidl_BaseInterface *_ex)

SIDL_C_INLINE_DECL void

bHYPRE_StructPFMG__**raddRef** (bHYPRE_StructPFMG self, sidl_BaseInterface *_ex)

On a remote object, addrefs the remote instance

SIDL_C_INLINE_DECL sidl_bool

bHYPRE_StructPFMG__isRemote (bHYPRE_StructPFMG self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

sidl_bool

bHYPRE_StructPFMG__isLocal (bHYPRE_StructPFMG self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

**_ex

Cast method for interface and class type conversions

7.3.10 **_ex

7.3.1 .

 $struct \ \ \mathbf{bHYPRE_StructPFMG__object}$

Symbol "bHYPRE.StructPFMG" (version 1.0.0)

Objects of this type can be cast to Solver objects using the __cast methods.

The StructPFMG solver requires a Struct matrix.

7.3.2

bHYPRE_StructPFMG bHYPRE_StructPFMG__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

___ 7.3.3 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_StructPFMG_SetOperator (bHYPRE_StructPFMG self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

_ 7.3.4 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_StructPFMG_SetTolerance (bHYPRE_StructPFMG self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

7.3.5

SIDL_C_INLINE_DECL int32_t bHYPRE_StructPFMG_SetMaxIterations (bHYPRE_StructPFMG self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

7.3.6

SIDL_C_INLINE_DECL int32_t bHYPRE_StructPFMG_SetLogging (bHYPRE_StructPFMG self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

 $_$ 7.3.7 $_$

SIDL_C_INLINE_DECL int32_t bHYPRE_StructPFMG_SetPrintLevel (bHYPRE_StructPFMG self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

_ 7.3.8 _

SIDL_C_INLINE_DECL int32_t bHYPRE_StructPFMG_SetCommunicator (bHYPRE_StructPFMG self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

 $_$ 7.3.9 $_$

SIDL_C_INLINE_DECL void bHYPRE_StructPFMG_Destroy (bHYPRE_StructPFMG self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

7.3.10

RMI connector function for the class. (no addref)

_ 7.4 _

Struct SMG Solver

Names		
7.4.1	struct bHYPRE_StructSMG_object Symbol "bHYPRE	195
	_ex	
	Constructor function for the class	
	bHYPRE_StructSMG bHYPRE_StructSMGcreateRemote (const char * url,	
	RMI constructor function for the class	
	bHYPRE_StructSMG bHYPRE_StructSMGwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_StructSMGdata) passed in rather than running the constructor	
7.4.2	bHYPRE_StructSMG bHYPRE_StructSMGconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	195
	bHYPRE_StructSMG bHYPRE_MPICommunicator mpi_comm, bHYPRE_StructMatrix A, sidl_BaseInterface *_ex)	
	This function is the preferred way to create a Struct SMG solver	
7.4.3	SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_SetOperator (bHYPRE_StructSMG self, bHYPRE_Operator A, sidl_BaseInterface *_ex)	
	Set the operator for the linear system being solved	195
7.4.4	SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_SetTolerance (bHYPRE_StructSMG self,	
	(Optional) Set the convergence tolerance	195
7.4.5	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_StructSMG_SetMaxIterations (bHYPRE_StructSMG self, int32_t max_iterations, sidl_BaseInterface *_ex)	
	(Optional) Set maximum number of iterations	196
7.4.6	SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_SetLogging (bHYPRE_StructSMG self,	
	(Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	196
7.4.7	SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_SetPrintLevel (bHYPRE_StructSMG self,	
	(Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	196
	SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_GetNumIterations (bHYPRE_StructSMG self, int32_t* num_iterations, sidl_BaseInterface *_ex)	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_GetRelResidualNorm (bHYPRE_StructSMG self,	
	double* norm, sidl_BaseInterface *_ex) (Optional) Return the norm of the relative residual	
7.4.8	SIDL_C_INLINE_DECL int32_t	
7.4.0	bHYPRE_StructSMG_SetCommunicator (bHYPRE_StructSMG self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)	
	Set the MPI Communicator	196
7.4.9	SIDL_C_INLINE_DECL void bHYPRE_StructSMG self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	197
	SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_SetIntParameter (bHYPRE_StructSMG self,	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_SetDoubleParameter (bHYPRE_StructSMG self,	
	const char* name, double value, sidl_BaseInterface *_ex)	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_StructSMG_SetStringParameter ( bHYPRE_StructSMG self,
                                             const char* name,
                                             const char* value,
                                             sidl_BaseInterface *_ex)
      Set the string parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructSMG_SetIntArray1Parameter ( bHYPRE_StructSMG self,
                                                 const char* name,
                                                 int32_t* value,
                                                 int32_t nvalues.
                                                 sidl_BaseInterface *_ex)
      Set the int 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructSMG_SetIntArray2Parameter ( bHYPRE_StructSMG self,
                                                 const char* name, struct
                                                 sidl_int_array* value,
                                                 sidl_BaseInterface *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructSMG_SetDoubleArray1Parameter (
                                                     bHYPRE_StructSMG
                                                     self.
                                                     const char* name,
                                                     double* value.
                                                     int32_t nvalues,
                                                     sidl_BaseInterface
                                                     *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructSMG_SetDoubleArray2Parameter (
                                                     bHYPRE_StructSMG
                                                     self.
                                                     const char* name,
                                                     struct
                                                     sidl_double_array*
                                                     value.
                                                     sidl\_BaseInterface
                                                     *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructSMG_GetIntValue ( bHYPRE_StructSMG self,
                                     const char* name, int32_t* value,
                                     sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructSMG_GetDoubleValue ( bHYPRE_StructSMG self,
                                          const char* name, double* value,
                                         sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL_int32_t
```

```
bHYPRE_StructSMG_Setup ( bHYPRE_StructSMG self,
                              bHYPRE_Vector b, bHYPRE_Vector x,
                              sidl_BaseInterface *_ex)
       (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructSMG_Apply ( bHYPRE_StructSMG self,
                              bHYPRE_Vector b, bHYPRE_Vector* x,
                              sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_StructSMG_ApplyAdjoint ( bHYPRE_StructSMG self,
                                      bHYPRE_Vector b,
                                      bHYPRE_Vector* x,
                                      sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_ex
      Cast method for interface and class type conversions
void*
bHYPRE_StructSMG__cast2 (void* obj, const char* type,
                              sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
bHYPRE_StructSMG__exec ( bHYPRE_StructSMG self,
                             const char* methodName, sidl_rmi_Call inArgs,
                             sidl_rmi_Return outArgs,
                             sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL_char*
bHYPRE_StructSMG__getURL ( bHYPRE_StructSMG self,
                                 sidl_BaseInterface *_ex)
      Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL void
bHYPRE_StructSMG__raddRef ( bHYPRE_StructSMG self,
                                 sidl_BaseInterface *_ex)
      On a remote object, addrefs the remote instance
SIDL_C_INLINE_DECL_sidl_bool
bHYPRE_StructSMG__isRemote ( bHYPRE_StructSMG self,
                                  sidl_BaseInterface *_ex)
      TRUE if this object is remote, false if local
sidl_bool
bHYPRE_StructSMG__isLocal ( bHYPRE_StructSMG self,
                                sidl_BaseInterface *_ex)
      TRUE if this object is remote, false if local
**_ex
      Cast method for interface and class type conversions
**_{-ex}
      RMI connector function for the class .....
                                                                               197
```

struct bHYPRE_StructSMG__object

 $Symbol "bHYPRE.StructSMG" \ (version \ 1.0.0)$

Objects of this type can be cast to Solver objects using the **__cast** methods.

The StructSMG solver requires a Struct matrix.

7.4.2

bHYPRE_StructSMG bHYPRE_StructSMG__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

__ 7.4.3 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_SetOperator (bHYPRE_StructSMG self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

_ 7.4.4 __

SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_SetTolerance (bHYPRE_StructSMG self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_SetMaxIterations (bHYPRE_StructSMG self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

__ 7.4.6 ____

SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_SetLogging (bHYPRE_StructSMG self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

7.4.7

SIDL_C_INLINE_DECL int32_t bHYPRE_StructSMG_SetPrintLevel (bHYPRE_StructSMG self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

__ 7.4.8 _____

SIDL_C_INLINE_DECL int32_t
bHYPRE_StructSMG_SetCommunicator (bHYPRE_StructSMG self,
bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

SIDL_C_INLINE_DECL void $\bf bHYPRE_StructSMG_Destroy$ (bHYPRE_StructSMG self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

7.4.10

RMI connector function for the class. (no addref)

_ 8

SemiStructured Matrix Solvers

Names		
3.1	SemiStruct DiagScale Solver	
		198
8.2	Struct Split Solver	-
		205
These solv	ers use semi-structured matrix/vector storage schemes.	
8.1		
		-
Sem	iStruct DiagScale Solver	
Names		
8.1.1	struct bHYPRE_SStructDiagScaleobject Symbol "bHYPRE	202
	_ex	
	Constructor function for the class	
	bHYPRE_SStructDiagScale bHYPRE_SStructDiagScalecreateRemote (const char * url,	
	RMI constructor function for the class	
	bHYPRE_SStructDiagScale bHYPRE_SStructDiagScalewrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_SStructDiagScaledata) passed in rather than running the constructor	
8.1.2	bHYPRE_SStructDiagScale bHYPRE_SStructDiagScaleconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	203
	bHYPRE_SStructDiagScale bHYPRE_SStructDiagScale_Create (bHYPRE_MPICommunicator mpi comm bHYPRE Operator A	200

sidl_BaseInterface *_ex)

This function is the preferred way to create a SStruct DiagScale solver

DOC++ is ©1995 by Roland Wunderling Malte Zöckler

 $SIDL_C_INLINE_DECL \ int 32_t$

8.1.3

	bHYPRE_SStructDiagScale_SetOperator (bHYPRE_SStructDiagScale self, bHYPRE_Operator A, sidl_BaseInterface *_ex)	
	,	203
8.1.4	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructDiagScale_SetTolerance (bHYPRE_SStructDiagScale self, double tolerance, sidl_BaseInterface *_ex)	
	,	203
8.1.5	SIDL_C_INLINE_DECL int32_t	
01210	${\bf bHYPRE_SStructDiagScale_SetMaxIterations} \ ($	
	bHYPRE_SStructDiagScale	
	self, int32_t max_iterations, sidl_BaseInterface *_ex)	
	,	203
8.1.6	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructDiagScale_SetLogging (bHYPRE_SStructDiagScale self, int32_t level,	
	sidl_BaseInterface *_ex) (Optional) Set the logging level, specifying the degree of additional informa-	
		204
8.1.7	SIDL_C_INLINE_DECL_int32_t bHYPRE_SStructDiagScale_SetPrintLevel (bHYPRE_SStructDiagScale	
	$\mathrm{self}, \mathrm{int} 32$ - $\mathrm{t} \ \mathrm{level},$	
	sidl_BaseInterface *_ex) (Optional) Set the print level, specifying the degree of informational data	
		204
	SIDL_C_INLINE_DECL int32_t	
	${\bf bHYPRE_SStructDiagScale_GetNumIterations}\ ($	
	bHYPRE_SStructDiagScale	
	$\operatorname{self}, \\ \operatorname{int} 32_{-\operatorname{t}}^* \operatorname{num_iterations},$	
	sidl_BaseInterface *_ex)	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_SStructDiagScale_GetRelResidualNorm (
	bHYPRE_SStructDiagScale self, double* norm, sidl_BaseInterface *_ex)	
	(Optional) Return the norm of the relative residual	
8.1.8	SIDL_C_INLINE_DECL_int32_t	
0.1.0	bHYPRE_SStructDiagScale_SetCommunicator (
	bHYPRE_SStructDiagScale	
	self,	
	bHYPRE_MPICommunicator mpi_comm,	
	sidl_BaseInterface *_ex)	
		204
8.1.9	SIDL_C_INLINE_DECL_void	

```
bHYPRE_SStructDiagScale_Destroy ( bHYPRE_SStructDiagScale self,
                                       sidl_BaseInterface *_ex)
       The Destroy function doesn't necessarily destroy anything ...
                                                                                  204
SIDL_C_INLINE_DECL int32_t
bHYPRE\_SStructDiagScale\_SetIntParameter ( bHYPRE\_SStructDiagScale
                                                self, const char* name,
                                                int32_t value,
                                                sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructDiagScale_SetDoubleParameter (
                                                     bHYPRE\_SStructDiagScale
                                                     self, const char* name,
                                                     double value,
                                                     sidl_BaseInterface *_ex)
      Set the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructDiagScale_SetStringParameter (
                                                    bHYPRE\_SStructDiagScale
                                                    self, const char* name,
                                                    const char* value,
                                                    sidl_BaseInterface *_ex)
      Set the string parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructDiagScale_SetIntArray1Parameter (
                                                        bHYPRE\_SStructDiagScale
                                                        self.
                                                        const char* name,
                                                        int32_t* value.
                                                        int32_t nvalues,
                                                        sidl_BaseInterface
                                                        *_ex)
      Set the int 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructDiagScale_SetIntArray2Parameter (
                                                        bHYPRE\_SStructDiagScale
                                                        self.
                                                        const char* name,
                                                        struct
                                                        sidl_int_array*
                                                        value,
                                                        sidl_BaseInterface
                                                        *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
```

```
bHYPRE_SStructDiagScale_SetDoubleArray1Parameter (
                                                            bHYPRE_SStructDiagScale
                                                           self, const
                                                           char* name,
                                                           double* value,
                                                           int32_t nvalues,
                                                           sidl_BaseInterface
                                                            *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructDiagScale_SetDoubleArray2Parameter (
                                                            bHYPRE_SStructDiagScale
                                                           self, const
                                                           char* name,
                                                           struct
                                                           sidl_double_array*
                                                            value,
                                                           sidl_BaseInterface
                                                            *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructDiagScale_GetIntValue ( bHYPRE_SStructDiagScale self,
                                           const char* name,
                                           int32_t* value,
                                           sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructDiagScale_GetDoubleValue ( bHYPRE_SStructDiagScale
                                                self, const char* name,
                                                double* value,
                                                sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructDiagScale_Setup ( bHYPRE_SStructDiagScale self,
                                    bHYPRE_Vector b, bHYPRE_Vector x,
                                    sidl_BaseInterface *_ex)
       (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructDiagScale_Apply ( bHYPRE_SStructDiagScale self,
                                     bHYPRE_Vector b,
                                     bHYPRE_Vector* x,
                                     sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructDiagScale_ApplyAdjoint ( bHYPRE_SStructDiagScale
                                             self, bHYPRE_Vector b,
                                             bHYPRE_Vector* x,
                                             sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_{-}ex
```

Cast method for interface and class type conversions

void*

bHYPRE_SStructDiagScale__cast2 (void* obj, const char* type, sidl_BaseInterface *_ex)

String cast method for interface and class type conversions

SIDL_C_INLINE_DECL void

bHYPRE_SStructDiagScale__exec (bHYPRE_SStructDiagScale self, const char* methodName,

sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex)

Select and execute a method by name

SIDL_C_INLINE_DECL char*

bHYPRE_SStructDiagScale__getURL (bHYPRE_SStructDiagScale self, sidl_BaseInterface *_ex)

Get the URL of the Implementation of this object (for RMI)

SIDL_C_INLINE_DECL void

bHYPRE_SStructDiagScale__raddRef (bHYPRE_SStructDiagScale self, sidl_BaseInterface *_ex)

On a remote object, addrefs the remote instance

 $SIDL_C_INLINE_DECL sidl_bool$

bHYPRE_SStructDiagScale__isRemote (bHYPRE_SStructDiagScale self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

sidl_bool

bHYPRE_SStructDiagScale__isLocal (bHYPRE_SStructDiagScale self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

**_ex

Cast method for interface and class type conversions

8.1.10 ******_**ex**

8.1.1

struct bHYPRE_SStructDiagScale__object

Symbol "bHYPRE.SStructDiagScale" (version 1.0.0)

_ 8.1.2 ____

bHYPRE_SStructDiagScale
bHYPRE_SStructDiagScale__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

8.1.3

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructDiagScale_SetOperator (bHYPRE_SStructDiagScale self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

8.1.4

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

 $_{-}$ 8.1.5 $_{-}$

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructDiagScale_SetMaxIterations (bHYPRE_SStructDiagScale self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

8.1.6

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructDiagScale_SetLogging (bHYPRE_SStructDiagScale self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

$_$ 8.1.7 $_$

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructDiagScale_SetPrintLevel (bHYPRE_SStructDiagScale self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

_ 8.1.8 _

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructDiagScale_SetCommunicator (bHYPRE_SStructDiagScale self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

_ 8.1.9 _

SIDL_C_INLINE_DECL void bHYPRE_SStructDiagScale self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

8.1.10

struct bHYPRE_SStructDiagScale__object* bHYPRE_SStructDiagScale__connectI const char * url sidl_bool ar struct sidl_BaseInterface__object **_ex

RMI connector function for the class. (no addref)

_ 8.2 .

Struct Split Solver

Names		
8.2.1	struct bHYPRE_SStructSplit_object Symbol "bHYPRE	209
	_ex Constructor function for the class	
	bHYPRE_SStructSplit bHYPRE_SStructSplitcreateRemote (const char * url,	
	RMI constructor function for the class	
	bHYPRE_SStructSplit bHYPRE_SStructSplitwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_SStructSplitdata) passed in rather than running the constructor	
8.2.2	bHYPRE_SStructSplit bHYPRE_SStructSplitconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	209
	bHYPRE_SStructSplit bHYPRE_MPICommunicator mpi_comm, bHYPRE_Operator A, sidl_BaseInterface *_ex) This function is the preferred way to create a SStruct Split solver	
8.2.3	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_SetOperator (bHYPRE_SStructSplit self,	
	,	209
8.2.4	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_SetTolerance (bHYPRE_SStructSplit self, double tolerance, sidl_BaseInterface *_ex)	
	· · · · · · · · · · · · · · · · · · ·	209
8.2.5	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_SStructSplit_SetMaxIterations (bHYPRE_SStructSplit self, int32_t max_iterations, sidl_BaseInterface *_ex)	
	(Optional) Set maximum number of iterations	210
8.2.6	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_SetLogging (bHYPRE_SStructSplit self,	
	(Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	210
8.2.7	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_SetPrintLevel (bHYPRE_SStructSplit self,	
	(Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	210
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_GetNumIterations (bHYPRE_SStructSplit self, int32_t* num_iterations, sidl_BaseInterface *_ex)	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_GetRelResidualNorm (bHYPRE_SStructSplit self,	
8.2.8	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_SetCommunicator (bHYPRE_SStructSplit self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)	210
	Set the MPI Communicator	210
8.2.9	SIDL_C_INLINE_DECL void bHYPRE_SStructSplit_Destroy (bHYPRE_SStructSplit self,	
	The Destroy function doesn't necessarily destroy anything	211
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_SetIntParameter (bHYPRE_SStructSplit self,	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_SetDoubleParameter (bHYPRE_SStructSplit self, const char* name, double value, sidl_BaseInterface *_ex)	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_SStructSplit_SetStringParameter ( bHYPRE_SStructSplit self,
                                               const char* name,
                                               const char* value,
                                               sidl_BaseInterface *_ex)
      Set the string parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructSplit_SetIntArray1Parameter ( bHYPRE_SStructSplit
                                                   self, const char* name,
                                                   int32_t* value,
                                                   int32_t nvalues.
                                                   sidl_BaseInterface *_ex)
      Set the int 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructSplit_SetIntArray2Parameter ( bHYPRE_SStructSplit
                                                   self, const char* name,
                                                   struct sidl_int_array*
                                                   value,
                                                   sidl_BaseInterface *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructSplit_SetDoubleArray1Parameter (
                                                       bHYPRE_SStructSplit
                                                       self.
                                                       const char* name,
                                                       double* value,
                                                       int32_t nvalues,
                                                       sidl_BaseInterface
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructSplit_SetDoubleArray2Parameter (
                                                       bHYPRE_SStructSplit
                                                       self,
                                                       const char* name,
                                                       struct
                                                       sidl\_double\_array*
                                                       value,
                                                       sidl\_BaseInterface
                                                       *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructSplit_GetIntValue ( bHYPRE_SStructSplit self,
                                       const char* name, int32_t* value,
                                       sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructSplit_GetDoubleValue ( bHYPRE_SStructSplit self,
                                           const char* name, double* value,
                                           sidl_BaseInterface *_ex)
       Get the double parameter associated with name
SIDL_C_INLINE_DECL_int32_t
```

```
bHYPRE_SStructSplit_Setup ( bHYPRE_SStructSplit self,
                               bHYPRE_Vector b, bHYPRE_Vector x,
                               sidl_BaseInterface *_ex)
       (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructSplit_Apply ( bHYPRE_SStructSplit self,
                                bHYPRE_Vector b, bHYPRE_Vector* x,
                                sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructSplit_ApplyAdjoint ( bHYPRE_SStructSplit self,
                                        bHYPRE_Vector b,
                                        bHYPRE_Vector* x,
                                        sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_ex
       Cast method for interface and class type conversions
void*
bHYPRE_SStructSplit__cast2 (void* obj, const char* type,
                               sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
bHYPRE_SStructSplit_exec ( bHYPRE_SStructSplit self,
                               const char* methodName,
                               sidl_rmi_Call inArgs, sidl_rmi_Return outArgs,
                               sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL_char*
bHYPRE_SStructSplit__getURL ( bHYPRE_SStructSplit self,
                                   sidl_BaseInterface *_ex)
       Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL void
bHYPRE_SStructSplit_raddRef ( bHYPRE_SStructSplit self,
                                   sidl_BaseInterface *_ex)
       On a remote object, addrefs the remote instance
SIDL_C_INLINE_DECL_sidl_bool
bHYPRE_SStructSplit__isRemote ( bHYPRE_SStructSplit self,
                                    sidl_BaseInterface *_ex)
       TRUE if this object is remote, false if local
sidl_bool
bHYPRE_SStructSplit__isLocal ( bHYPRE_SStructSplit self,
                                 sidl_BaseInterface *_ex)
       TRUE if this object is remote, false if local
**_ex
       Cast method for interface and class type conversions
**_{-ex}
       RMI connector function for the class .....
                                                                                 211
```

8.2.10

__ 8.2.1 __

struct bHYPRE_SStructSplit_object

Symbol "bHYPRE.SStructSplit" (version 1.0.0)

The SStructSplit solver requires a SStruct matrix.

_ 8.2.2 _

bHYPRE_SStructSplit bHYPRE_SStructSplit_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

_ 8.2.3 _

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_SetOperator (bHYPRE_SStructSplit self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

8.2.4

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_SetTolerance (bHYPRE_SStructSplit self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

8.2.5

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_SetMaxIterations (bHYPRE_SStructSplit self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

__ 8.2.6 _____

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

8.2.7

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_SetPrintLevel (bHYPRE_SStructSplit self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

__ 8.2.8 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructSplit_SetCommunicator (bHYPRE_SStructSplit self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

8.2.9

SIDL_C_INLINE_DECL void **bHYPRE_SStructSplit_Destroy** (bHYPRE_SStructSplit self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

8.2.10

RMI connector function for the class. (no addref)

9

PreconditionedSolver Interface

```
Names
9.1
            struct bHYPRE_PreconditionedSolver_object
                  Symbol "bHYPRE .....
                                                                                          213
9.2
            extern C bHYPRE_PreconditionedSolver
            bHYPRE_PreconditionedSolver_connect (const char *,
                                                      sidl_BaseInterface *_ex)
                  RMI connector function for the class .....
                                                                                          213
            SIDL_C_INLINE_DECL int32_t
            {\bf bHYPRE\_PreconditionedSolver\_SetPreconditioner} \ (
                                                               bHYPRE_PreconditionedSolver
                                                               self.
                                                               bHYPRE_Solver s,
                                                               sidl_BaseInterface
                                                                *_ex)
                  Set the preconditioner
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_PreconditionedSolver_GetPreconditioner (
                                                                bHYPRE_PreconditionedSolver
                                                                self.
                                                                bHYPRE_Solver* s,
                                                                sidl_BaseInterface
                                                                *_ex)
                  Method: GetPreconditioner[]
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_PreconditionedSolver_Clone ( bHYPRE_PreconditionedSolver
                                                   bHYPRE\_PreconditionedSolver* \ x,
                                                   sidl_BaseInterface *_ex)
                  Method: Clone[]
            _{\mathbf{ex}}
                  Cast method for interface and class type conversions
            void*
            bHYPRE_PreconditionedSolver_cast2 (void* obj, const char* type,
                                                   sidl_BaseInterface *_ex)
                  String cast method for interface and class type conversions
            SIDL_C_INLINE_DECL_void
            bHYPRE_PreconditionedSolver_exec ( bHYPRE_PreconditionedSolver self,
                                                   const char* methodName,
                                                   sidl_rmi_Call inArgs,
                                                   sidl_rmi_Return outArgs,
                                                   sidl\_BaseInterface *\_ex)
                  Select and execute a method by name
            SIDL_C_INLINE_DECL char*
```

bHYPRE_PreconditionedSolver_getURL (bHYPRE_PreconditionedSolver self, sidl_BaseInterface *_ex) Get the URL of the Implementation of this object (for RMI) SIDL_C_INLINE_DECL void bHYPRE_PreconditionedSolver_raddRef (bHYPRE_PreconditionedSolver self, sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance SIDL_C_INLINE_DECL sidl_bool bHYPRE_PreconditionedSolver__isRemote (bHYPRE_PreconditionedSolver self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local $sidl_bool$ $b HYPRE_Preconditioned Solver__isLocal \left(\begin{array}{c} b HYPRE_Preconditioned Solver \\ \end{array} \right)$ sidl_BaseInterface *_ex) TRUE if this object is remote, false if local $**_{-}ex$ Cast method for interface and class type conversions 9.3 $**_ex$ RMI connector function for the class 214

9.1

struct bHYPRE_PreconditionedSolver_object

Symbol "bHYPRE.PreconditionedSolver" (version 1.0.0)

9.2

extern C bHYPRE_PreconditionedSolver bHYPRE_PreconditionedSolver_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

93

RMI connector function for the class. (no addref)

__ 10

Preconditioned Solvers

.1	PCG Preconditioned Solver	
		21
2	GMRES Preconditioned Solver	22
3	BiCGSTAB Preconditioned Solver	212
		22
:	CGNR Preconditioned Solver	
		23

PCG Preconditioned Solver

Names		
10.1.1	struct bHYPRE_PCGobject Symbol "bHYPRE	219
	_ex Constructor function for the class	
	bHYPRE_PCG bHYPRE_PCGcreateRemote (const char * url, sidl_BaseInterface *_ex) RMI constructor function for the class	
	bHYPRE_PCG bHYPRE_PCGwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_PCGdata) passed in rather than running the constructor	
10.1.2	bHYPRE_PCG bHYPRE_PCGconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	219
	bHYPRE_PCG bHYPRE_MPICommunicator mpi_comm, bHYPRE_Operator A, sidl_BaseInterface *_ex) This function is the preferred way to create a PCG solver	
	SIDL_C_INLINE_DECL_int32_t	

	bHYPRE_PCG_SetPreconditioner (bHYPRE_PCG self, bHYPRE_Solver s,	
	${\it sidl_BaseInterface *_ex)} \\ Set \ the \ preconditioner$	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_PCG_GetPreconditioner (bHYPRE_PCG self, bHYPRE_Solver* s, sidl_BaseInterface *_ex)	
	Method: GetPreconditioner[]	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_PCG_Clone (bHYPRE_PCG self,	
	Method: Clone[]	
10.1.3	SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetOperator (bHYPRE_PCG self, bHYPRE_Operator A, sidl_BaseInterface *_ex)	
	Set the operator for the linear system being solved	219
10.1.4	SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetTolerance (bHYPRE_PCG self, double tolerance, sidl_BaseInterface *_ex)	
	(Optional) Set the convergence tolerance	219
10.1.5	SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetMaxIterations (bHYPRE_PCG self,	
	(Optional) Set maximum number of iterations	220
10.1.6	SIDL_C_INLINE_DECL_int32_t bHYPRE_PCG_SetLogging (bHYPRE_PCG self, int32_t level,	
	(Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	220
10.1.7	SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetPrintLevel (bHYPRE_PCG self, int32_t level,	
	(Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	220
	SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_GetNumIterations (bHYPRE_PCG self,	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_PCG_GetRelResidualNorm (bHYPRE_PCG self, double* norm, sidl_BaseInterface *_ex)	
	(Optional) Return the norm of the relative residual	
10.1.8	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_PCG_SetCommunicator (bHYPRE_PCG self, bHYPRE_MPICommunicator mpi_comm,	
	sidl_BaseInterface *_ex)	
	Set the MPI Communicator	220
10.1.9	SIDL_C_INLINE_DECL_void bHYPRE_PCG_Destroy (bHYPRE_PCG self, sidl_BaseInterface *_ex) The Destroy function doesn't necessarily destroy anything	221
	SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetIntParameter (bHYPRE_PCG self, const char* name, int32_t value, sidl_BaseInterface *_ex)	
	Set the int parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetDoubleParameter (bHYPRE_PCG self,	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetStringParameter (bHYPRE_PCG self,	
	Set the string parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetIntArray1Parameter (bHYPRE_PCG self,	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_PCG_SetIntArray2Parameter (bHYPRE_PCG self, const char* name, struct sidl_intarray* value, sidl_BaseInterface *_ex)	
	Set the int 2-D array parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetDoubleArray1Parameter (bHYPRE_PCG self,	
	Set the double 1-D array parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetDoubleArray2Parameter (bHYPRE_PCG self,	
	sidl_BaseInterface *_ex)	
	Set the double 2-D array parameter associated with name	
	SIDL C INLINE DECL. int32 t	

```
b HYPRE\_PCG\_GetIntValue \ ( \ bHYPRE\_PCG \ self, \ const \ char^* \ name,
                              int32_t* value, sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_PCG_GetDoubleValue ( bHYPRE_PCG self, const char* name,
                                  double* value, sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_PCG_Setup ( bHYPRE_PCG self, bHYPRE_Vector b,
                        bHYPRE_Vector x, sidl_BaseInterface *_ex)
       (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_PCG_Apply ( bHYPRE_PCG self, bHYPRE_Vector b,
                        bHYPRE_Vector* x, sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL_int32_t
bHYPRE_PCG_ApplyAdjoint ( bHYPRE_PCG self, bHYPRE_Vector b,
                                bHYPRE_Vector* x, sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_{\mathbf{ex}}
      Cast method for interface and class type conversions
void*
bHYPRE_PCG__cast2 (void* obj, const char* type, sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
bHYPRE_PCG__exec ( bHYPRE_PCG self, const char* methodName,
                       sidl_rmi_Call inArgs, sidl_rmi_Return outArgs,
                       sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL_char*
bHYPRE_PCG__getURL ( bHYPRE_PCG self, sidl_BaseInterface *_ex)
      Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL void
bHYPRE_PCG__raddRef ( bHYPRE_PCG self, sidl_BaseInterface *_ex)
      On a remote object, addrefs the remote instance
SIDL_C_INLINE_DECL sidl_bool
bHYPRE_PCG__isRemote ( bHYPRE_PCG self, sidl_BaseInterface *_ex)
      TRUE if this object is remote, false if local
sidl_bool
bHYPRE_PCG__isLocal ( bHYPRE_PCG self, sidl_BaseInterface *_ex)
       TRUE if this object is remote, false if local
**_ex
      Cast method for interface and class type conversions
**_ex
      RMI connector function for the class .....
                                                                                221
```

struct bHYPRE_PCG__object

Symbol "bHYPRE.PCG" (version 1.0.0)

PCG solver. This calls Babel-interface matrix and vector functions, so it will work with any consistent matrix, vector, and preconditioner classes.

___ 10.1.2 _____

bHYPRE_PCG bHYPRE_PCG__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

_ 10.1.3 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetOperator (bHYPRE_PCG self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

10.1.4

SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetTolerance (bHYPRE_PCG self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetMaxIterations (bHYPRE_PCG self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

__ 10.1.6 _____

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

10.1.7

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

10.1.8

SIDL_C_INLINE_DECL int32_t bHYPRE_PCG_SetCommunicator (bHYPRE_PCG self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

SIDL_C_INLINE_DECL void bHYPRE_PCG_Destroy (bHYPRE_PCG self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

___ 10.1.10 ____

RMI connector function for the class. (no addref)

_ 10.2 _

GMRES Preconditioned Solver

Names		
10.2.1	struct bHYPRE_GMRESobject Symbol "bHYPRE	225
	_ex Constructor function for the class	
	bHYPRE_GMRES bHYPRE_GMREScreateRemote (const char * url, sidl_BaseInterface *_ex) RMI constructor function for the class	
	bHYPRE_GMRES bHYPRE_GMRESwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_GMRESdata) passed in rather than running the constructor	
10.2.2	bHYPRE_GMRES bHYPRE_GMRESconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	225
	bHYPRE_GMRES bHYPRE_MPICommunicator mpi_comm, bHYPRE_Operator A, sidl_BaseInterface *_ex) This function is the preferred way to create a GMRES solver	
	SIDL_C_INLINE_DECL_int32_t	

	bHYPRE_GMRES_SetPreconditioner (bHYPRE_GMRES self, bHYPRE_Solver s,	
	sidl_BaseInterface *_ex)	
	Set the preconditioner	
	SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_GetPreconditioner (bHYPRE_GMRES self,	
	bHYPRE_Solver* s, sidl_BaseInterface *_ex) Method: GetPreconditioner[]	
	SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_Clone (bHYPRE_GMRES self,	
	bHYPRE_PreconditionedSolver* x, sidl_BaseInterface *_ex)	
	Method: Clone[]	
10.2.3	SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_SetOperator (bHYPRE_GMRES self, bHYPRE_Operator A,	
	sidl_BaseInterface *_ex)	225
	Set the operator for the linear system being solved	225
10.2.4	SIDL_C_INLINE_DECL_int32_t bHYPRE_GMRES_SetTolerance (bHYPRE_GMRES self,	
	(Optional) Set the convergence tolerance	226
10.2.5	SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_SetMaxIterations (bHYPRE_GMRES self,	
	sidl_BaseInterface *_ex) (Optional) Set maximum number of iterations	226
10.2.6	SIDL_C_INLINE_DECL int32_t	
10.2.0	bHYPRE_GMRES_SetLogging (bHYPRE_GMRES self, int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	226
10.2.7	SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_SetPrintLevel (bHYPRE_GMRES self, int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	226
	SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_GetNumIterations (bHYPRE_GMRES self,	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_GMRES_GetRelResidualNorm (bHYPRE_GMRES self, double* norm, sidl_BaseInterface *_ex)	
	(Optional) Return the norm of the relative residual	
10.2.8	SIDL_C_INLINE_DECL_int32_t	

	bHYPRE_GMRES_SetCommunicator (bHYPRE_GMRES self,	
	bHYPRE_MPICommunicator	
	mpi_comm, sidl_BaseInterface *_ex) Set the MPI Communicator	22'
10.00	SIDL_C_INLINE_DECL_void	22
10.2.9	bHYPRE_GMRES_Destroy (bHYPRE_GMRES self,	
	sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	227
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_GMRES_SetIntParameter (bHYPRE_GMRES self,	
	const char* name, int32_t value,	
	sidl_BaseInterface *_ex) Set the int parameter associated with name	
	-	
	SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_SetDoubleParameter (bHYPRE_GMRES self,	
	const char* name, double value,	
	sidl_BaseInterface *_ex)	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	
	$\mathbf{bHYPRE_GMRES_SetStringParameter} \ (\ \ \mathbf{bHYPRE_GMRES} \ \mathbf{self},$	
	const char* name,	
	const char* value,	
	sidl_BaseInterface *_ex) Set the string parameter associated with name	
	¥ -	
	SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_SetIntArray1Parameter (bHYPRE_GMRES self,	
	const char* name,	
	$int32t^*$ value,	
	int32_t nvalues,	
	sidl_BaseInterface *_ex) Set the int 1-D array parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_SetIntArray2Parameter (bHYPRE_GMRES self,	
	const char* name,	
	struct sidl_intarray* value,	
	sidl_BaseInterface *_ex)	
	Set the int 2-D array parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_GMRES_SetDoubleArray1Parameter (bHYPRE_GMRES self,	
	const char* name, double* value,	
	int32_t nvalues,	
	sidl_BaseInterface *_ex)	
	Set the double 1-D array parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_GMRES_SetDoubleArray2Parameter ( bHYPRE_GMRES self.
                                                 const char* name, struct
                                                 sidl_double_array* value,
                                                 sidl_BaseInterface *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_GMRES_GetIntValue ( bHYPRE_GMRES self,
                                 const char* name, int32_t* value,
                                 sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_GMRES_GetDoubleValue ( bHYPRE_GMRES self,
                                      const char* name, double* value,
                                      sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_GMRES_Setup ( bHYPRE_GMRES self, bHYPRE_Vector b,
                           bHYPRE_Vector x, sidl_BaseInterface *_ex)
      (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_GMRES_Apply ( bHYPRE_GMRES self, bHYPRE_Vector b,
                           bHYPRE_Vector* x, sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_GMRES_ApplyAdjoint ( bHYPRE_GMRES self,
                                   bHYPRE_Vector b, bHYPRE_Vector* x,
                                   sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_{-}\mathbf{ex}
      Cast method for interface and class type conversions
void*
bHYPRE_GMRES__cast2 (void* obj, const char* type,
                           sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL_void
bHYPRE_GMRES__exec ( bHYPRE_GMRES self,
                          const char* methodName, sidl_rmi_Call inArgs,
                          sidl_rmi_Return outArgs, sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL char*
bHYPRE_GMRES__getURL ( bHYPRE_GMRES self.
                              sidl_BaseInterface *_ex)
      Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL_void
bHYPRE_GMRES__raddRef ( bHYPRE_GMRES self,
                              sidl_BaseInterface *_ex)
      On a remote object, addrefs the remote instance
SIDL_C_INLINE_DECL_sidl_bool
```

bHYPRE_GMRES__isRemote (bHYPRE_GMRES self,

sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

sidl_bool

${\bf bHYPRE_GMRES_isLocal} \ (\ \ {\bf bHYPRE_GMRES} \ {\bf self},$

sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

 $**_{-}ex$

Cast method for interface and class type conversions

10.2.10 **_ex

10.2.1

struct bHYPRE_GMRES__object

Symbol "bHYPRE.GMRES" (version 1.0.0)

GMRES solver. This calls Babel-interface matrix and vector functions, so it will work with any consistent matrix, vector, and preconditioner classes.

 $_{-}$ 10.2.2 $_{-}$

bHYPRE_GMRES
bHYPRE_GMRES__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

__ 10.2.3 ___

SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_SetOperator (bHYPRE_GMRES self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

10.2.4

SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_SetTolerance (bHYPRE_GMRES self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

__ 10.2.5 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_SetMaxIterations (bHYPRE_GMRES self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

_ 10.2.6 ___

(Optional) Set the $logging\ level$, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

10.2.7

SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_SetPrintLevel (bHYPRE_GMRES self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

10.2.8

SIDL_C_INLINE_DECL int32_t bHYPRE_GMRES_SetCommunicator (bHYPRE_GMRES self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

10.2.9

SIDL_C_INLINE_DECL void bHYPRE_GMRES_Destroy (bHYPRE_GMRES self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

__ 10.2.10 _____

struct bHYPRE_GMRES__object* bHYPRE_GMRES__connectI const char * url sidl_bool ar struct sidl_BaseInterface_object
**_ex

RMI connector function for the class. (no addref)

__ 10.3 ___

BiCGSTAB Preconditioned Solver

Names

 $10.3.1 \hspace{1.5cm} \textbf{struct} \hspace{0.2cm} \textbf{bHYPRE_BiCGSTAB__object}$

 $_{\mathbf{ex}}$

Constructor function for the class

bHYPRE_BiCGSTAB

	bHYPRE_BiCGSTABcreateRemote (const char * url, sidl_BaseInterface *_ex)	
	RMI constructor function for the class	
	bHYPRE_BiCGSTAB bHYPRE_BiCGSTABwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_BiCGSTABdata) passed in rather than running the constructor	
10.3.2	bHYPRE_BiCGSTAB bHYPRE_BiCGSTABconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	232
	bHYPRE_BiCGSTAB bHYPRE_BiCGSTAB_Create (bHYPRE_MPICommunicator mpi_comm, bHYPRE_Operator A, sidl_BaseInterface *_ex) This function is the preferred way to create a BiCGSTAB solver	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_BiCGSTAB_SetPreconditioner (bHYPRE_BiCGSTAB self, bHYPRE_Solver s, sidl_BaseInterface *_ex)	
	Set the preconditioner	
	SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_GetPreconditioner (bHYPRE_BiCGSTAB self, bHYPRE_Solver* s, sidl_BaseInterface *_ex)	
	$Method: \ GetPreconditioner[]$	
	SIDL_C_INLINE_DECL_int32_t bHYPRE_BiCGSTAB_Clone (bHYPRE_BiCGSTAB self, bHYPRE_PreconditionedSolver* x, sidl_BaseInterface *_ex)	
10.00	Method: Clone[]	
10.3.3	SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_SetOperator (bHYPRE_BiCGSTAB self, bHYPRE_Operator A, sidl_BaseInterface *_ex)	
	Set the operator for the linear system being solved	232
10.3.4	SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_SetTolerance (bHYPRE_BiCGSTAB self, double tolerance, sidl_BaseInterface *_ex)	
	(Optional) Set the convergence tolerance	232
10.3.5	SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_SetMaxIterations (bHYPRE_BiCGSTAB self, int32_t max_iterations, sidl_BaseInterface *_ex)	
	(Optional) Set maximum number of iterations	233
10.3.6	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_BiCGSTAB_SetLogging (bHYPRE_BiCGSTAB self, int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the logging level, specifying the degree of additional informational data to be accumulated	233
10.3.7	SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_SetPrintLevel (bHYPRE_BiCGSTAB self,	
	to be printed either to the screen or to a file	233
	SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_GetNumIterations (bHYPRE_BiCGSTAB self, int32_t* num_iterations, sidl_BaseInterface *_ex)	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_GetRelResidualNorm (bHYPRE_BiCGSTAB self, double* norm, sidl_BaseInterface *_ex)	
	(Optional) Return the norm of the relative residual	
10.3.8	SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_SetCommunicator (bHYPRE_BiCGSTAB self, bHYPRE_MPICommunicator	
	mpi_comm, sidl_BaseInterface *_ex)	
	Set the MPI Communicator	233
10.3.9	SIDL_C_INLINE_DECL void bHYPRE_BiCGSTAB_Destroy (bHYPRE_BiCGSTAB self,	
	The Destroy function doesn't necessarily destroy anything	234
	SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_SetIntParameter (bHYPRE_BiCGSTAB self,	
	sidl_BaseInterface *_ex) Set the int parameter associated with name	
	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_BiCGSTAB_SetDoubleParameter (bHYPRE_BiCGSTAB self, const char* name, double value, sidl_BaseInterface *_ex)	
	Set the double parameter associated with name	
	SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_SetStringParameter (bHYPRE_BiCGSTAB self, const char* name, const char* value, sidl_BaseInterface *_ex)	
	Set the string parameter associated with name	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_BiCGSTAB_SetIntArray1Parameter ( bHYPRE_BiCGSTAB
                                                 self, const char* name,
                                                 int32_t* value,
                                                 int32_t nvalues,
                                                 sidl_BaseInterface *_ex)
      Set the int 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_BiCGSTAB_SetIntArray2Parameter ( bHYPRE_BiCGSTAB
                                                 self, const char* name,
                                                 struct sidl_int_array*
                                                 value.
                                                 sidl_BaseInterface *_ex)
      Set the int 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_BiCGSTAB_SetDoubleArray1Parameter (
                                                     bHYPRE_BiCGSTAB
                                                     self.
                                                     const char* name,
                                                     double* value,
                                                     int32_t nvalues,
                                                     sidl_BaseInterface
                                                     *_ex)
      Set the double 1-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_BiCGSTAB_SetDoubleArray2Parameter (
                                                     bHYPRE_BiCGSTAB
                                                     self,
                                                     const char* name.
                                                     struct
                                                     sidl_double_array*
                                                     value,
                                                     sidl_BaseInterface
                                                     *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_BiCGSTAB_GetIntValue ( bHYPRE_BiCGSTAB self,
                                     const char* name, int32_t* value,
                                     sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_BiCGSTAB_GetDoubleValue ( bHYPRE_BiCGSTAB self,
                                         const char* name, double* value,
                                         sidl_BaseInterface *_ex)
      Get\ the\ double\ parameter\ associated\ with\ {\tt name}
SIDL_C_INLINE_DECL int32_t
bHYPRE_BiCGSTAB_Setup ( bHYPRE_BiCGSTAB self,
                              bHYPRE_Vector b, bHYPRE_Vector x,
                              sidl_BaseInterface *_ex)
      (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
```

```
bHYPRE_BiCGSTAB_Apply ( bHYPRE_BiCGSTAB self,
                               bHYPRE_Vector b, bHYPRE_Vector* x,
                               sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_BiCGSTAB_ApplyAdjoint ( bHYPRE_BiCGSTAB self,
                                       bHYPRE_Vector b,
                                       bHYPRE_Vector* x.
                                       sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_{\mathbf{ex}}
      Cast method for interface and class type conversions
void*
bHYPRE_BiCGSTAB__cast2 (void* obj, const char* type,
                               sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
bHYPRE_BiCGSTAB__exec ( bHYPRE_BiCGSTAB self,
                              const char* methodName, sidl_rmi_Call inArgs,
                              sidl_rmi_Return outArgs,
                              sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL char*
bHYPRE_BiCGSTAB__getURL ( bHYPRE_BiCGSTAB self,
                                  sidl_BaseInterface *_ex)
      Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL_void
bHYPRE_BiCGSTAB__raddRef ( bHYPRE_BiCGSTAB self,
                                  sidl_BaseInterface *_ex)
      On a remote object, addrefs the remote instance
SIDL_C_INLINE_DECL sidl_bool
bHYPRE_BiCGSTAB__isRemote ( bHYPRE_BiCGSTAB self,
                                   sidl_BaseInterface *_ex)
      TRUE if this object is remote, false if local
sidl\_bool
bHYPRE_BiCGSTAB__isLocal ( bHYPRE_BiCGSTAB self,
                                 sidl_BaseInterface *_ex)
       TRUE if this object is remote, false if local
**_ex
      Cast method for interface and class type conversions
**_ex
```

RMI connector function for the class

10.3.10

234

__ 10.3.1 _____

struct bHYPRE_BiCGSTAB__object

Symbol "bHYPRE.BiCGSTAB" (version 1.0.0)

BiCGSTAB solver. This calls Babel-interface matrix and vector functions, so it will work with any consistent matrix, vector, and preconditioner classes.

__ 10.3.2 ____

bHYPRE_BiCGSTAB bHYPRE_BiCGSTAB__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

10.3.3

SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_SetOperator (bHYPRE_BiCGSTAB self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

10.3.4

SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_SetTolerance (bHYPRE_BiCGSTAB self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

10.3.5

SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_SetMaxIterations (bHYPRE_BiCGSTAB self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

__ 10.3.6 _____

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

10.3.7

SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_SetPrintLevel (bHYPRE_BiCGSTAB self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

10.3.8

SIDL_C_INLINE_DECL int32_t bHYPRE_BiCGSTAB_SetCommunicator (bHYPRE_BiCGSTAB self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

10.3.9

SIDL_C_INLINE_DECL_void **bHYPRE_BiCGSTAB_Destroy** (bHYPRE_BiCGSTAB self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

10.3.10

RMI connector function for the class. (no addref)

__ 10.4 __

CGNR Preconditioned Solver

Names

10.4.1	struct bHYPRE_CGNRobject Symbol "bHYPRE	238
	_ex Constructor function for the class	
	bHYPRE_CGNR bHYPRE_CGNRcreateRemote (const char * url, sidl_BaseInterface *_ex) RMI constructor function for the class	
	bHYPRE_CGNR bHYPRE_CGNRwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_CGNRdata) passed in rather than running the constructor	
10.4.2	bHYPRE_CGNR bHYPRE_CGNRconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	238
	bHYPRE_CGNR	

	bHYPRE_CGNR_Create (bHYPRE_MPICommunicator mpi_comm,	
	bHYPRE_Operator A, sidl_BaseInterface *_ex) This function is the preferred way to create a CGNR solver	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_CGNR_SetPreconditioner (bHYPRE_CGNR self,	
	bHYPRE_Solver s,	
	sidl_BaseInterface *_ex)	
	Set the preconditioner	
	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_CGNR_GetPreconditioner (bHYPRE_CGNR self, bHYPRE_Solver* s,	
	sidl_BaseInterface *_ex)	
	$Method: \ GetPreconditioner[]$	
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_CGNR_Clone (bHYPRE_CGNR self,	
	bHYPRE_PreconditionedSolver* x,	
	sidl_BaseInterface *_ex) Method: Clone/	
10.4.3	SIDL_C_INLINE_DECL_int32_t bHYPRE_CGNR_SetOperator (bHYPRE_CGNR self,	
	bHYPRE_Operator A,	
	sidl_BaseInterface *_ex)	
	Set the operator for the linear system being solved	238
10.4.4	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_CGNR_SetTolerance (bHYPRE_CGNR self, double tolerance,	
	sidl_BaseInterface *_ex) (Optional) Set the convergence tolerance	239
10.4.5	SIDL_C_INLINE_DECL int32_t	200
10.4.9	bHYPRE_CGNR_SetMaxIterations (bHYPRE_CGNR self,	
	int32_t max_iterations,	
	sidl_BaseInterface *_ex)	
	(Optional) Set maximum number of iterations	239
10.4.6	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_CGNR_SetLogging (bHYPRE_CGNR self, int32_t level, sidl_BaseInterface *_ex)	
	(Optional) Set the logging level, specifying the degree of additional informa-	
	tional data to be accumulated	239
10.4.7	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_CGNR_SetPrintLevel (bHYPRE_CGNR self, int32_t level,	
	sidl_BaseInterface *_ex)	
	(Optional) Set the print level, specifying the degree of informational data to be printed either to the screen or to a file	239
	· · · · · · · · · · · · · · · · · · ·	238
	SIDL_C_INLINE_DECL int32_t bHYPRE_CGNR_GetNumIterations (bHYPRE_CGNR self,	
	int32_t* num_iterations,	
	sidl_BaseInterface *_ex)	
	(Optional) Return the number of iterations taken	
	SIDL_C_INLINE_DECL int32_t	

```
bHYPRE_CGNR_GetRelResidualNorm ( bHYPRE_CGNR self,
                                                    double* norm,
                                                    sidl_BaseInterface *_ex)
                  (Optional) Return the norm of the relative residual
10.4.8
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_CGNR_SetCommunicator ( bHYPRE_CGNR self,
                                                 bHYPRE_MPICommunicator
                                                mpi_comm, sidl_BaseInterface *_ex)
                  Set the MPI Communicator .....
                                                                                         240
10.4.9
            SIDL_C_INLINE_DECL void
            bHYPRE_CGNR_Destroy ( bHYPRE_CGNR self, sidl_BaseInterface *_ex)
                  The Destroy function doesn't necessarily destroy anything .....
                                                                                         240
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_CGNR_SetIntParameter ( bHYPRE_CGNR self,
                                               const char* name, int32_t value,
                                               sidl_BaseInterface *_ex)
                  Set the int parameter associated with name
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_CGNR_SetDoubleParameter ( bHYPRE_CGNR self,
                                                   const char* name, double value,
                                                   sidl_BaseInterface *_ex)
                  Set the double parameter associated with name
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_CGNR_SetStringParameter ( bHYPRE_CGNR self,
                                                  const char* name,
                                                  const char* value,
                                                  sidl_BaseInterface *_ex)
                  Set the string parameter associated with name
            SIDL_C_INLINE_DECL int32_t
           bHYPRE_CGNR_SetIntArray1Parameter ( bHYPRE_CGNR self,
                                                      const char* name.
                                                      int32_t* value, int32_t nvalues,
                                                      sidl_BaseInterface *_ex)
                  Set the int 1-D array parameter associated with name
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_CGNR_SetIntArray2Parameter ( bHYPRE_CGNR self,
                                                      const char* name,
                                                      struct sidl_int_array* value,
                                                      sidl_BaseInterface *_ex)
                  Set the int 2-D array parameter associated with name
            SIDL_C_INLINE_DECL int32_t
            bHYPRE_CGNR_SetDoubleArray1Parameter ( bHYPRE_CGNR self,
                                                          const char* name,
                                                          double* value.
                                                          int32_t nvalues,
                                                          sidl_BaseInterface *_ex)
                  Set the double 1-D array parameter associated with name
            SIDL_C_INLINE_DECL int32_t
```

```
bHYPRE_CGNR_SetDoubleArray2Parameter ( bHYPRE_CGNR self.
                                                const char* name, struct
                                                sidl_double_array* value,
                                                sidl_BaseInterface *_ex)
      Set the double 2-D array parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_CGNR_GetIntValue ( bHYPRE_CGNR self, const char* name,
                                int32_t* value, sidl_BaseInterface *_ex)
      Set the int parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_CGNR_GetDoubleValue ( bHYPRE_CGNR self,
                                    const char* name, double* value,
                                    sidl_BaseInterface *_ex)
      Get the double parameter associated with name
SIDL_C_INLINE_DECL int32_t
bHYPRE_CGNR_Setup ( bHYPRE_CGNR self, bHYPRE_Vector b,
                         bHYPRE_Vector x, sidl_BaseInterface *_ex)
       (Optional) Do any preprocessing that may be necessary in order to execute
      Apply
SIDL_C_INLINE_DECL int32_t
bHYPRE_CGNR_Apply ( bHYPRE_CGNR self, bHYPRE_Vector b,
                          bHYPRE_Vector* x, sidl_BaseInterface *_ex)
      Apply the operator to b, returning x
SIDL_C_INLINE_DECL int32_t
bHYPRE_CGNR_ApplyAdjoint ( bHYPRE_CGNR self,
                                 bHYPRE_Vector b, bHYPRE_Vector* x,
                                 sidl_BaseInterface *_ex)
      Apply the adjoint of the operator to b, returning x
_{\mathbf{ex}}
      Cast method for interface and class type conversions
void*
bHYPRE_CGNR__cast2 (void* obj, const char* type,
                         sidl_BaseInterface *_ex)
      String cast method for interface and class type conversions
SIDL_C_INLINE_DECL void
bHYPRE_CGNR__exec ( bHYPRE_CGNR self, const char* methodName,
                         sidl_rmi_Call inArgs, sidl_rmi_Return outArgs,
                         sidl_BaseInterface *_ex)
      Select and execute a method by name
SIDL_C_INLINE_DECL char*
bHYPRE_CGNR__getURL ( bHYPRE_CGNR self, sidl_BaseInterface *_ex)
      Get the URL of the Implementation of this object (for RMI)
SIDL_C_INLINE_DECL_void
```

bHYPRE_CGNR__raddRef (bHYPRE_CGNR self, sidl_BaseInterface *_ex)

On a remote object, addrefs the remote instance

DOC++ is ©1995 by Roland Wunderling Malte Zöckler

SIDL_C_INLINE_DECL_sidl_bool

bHYPRE_CGNR__isRemote (bHYPRE_CGNR self,

sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

sidl_bool

bHYPRE_CGNR__isLocal (bHYPRE_CGNR self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

 $**_ex$

Cast method for interface and class type conversions

10.4.10 **_ex

_ 10.4.1 ___

struct bHYPRE_CGNR__object

Symbol "bHYPRE.CGNR" (version 1.0.0)

CGNR solver. This calls Babel-interface matrix and vector functions, so it will work with any consistent matrix, vector, and preconditioner classes.

10.4.2

bHYPRE_CGNR bHYPRE_CGNR__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

10.4.3

SIDL_C_INLINE_DECL int32_t bHYPRE_CGNR_SetOperator (bHYPRE_CGNR self, bHYPRE_Operator A, sidl_BaseInterface *_ex)

Set the operator for the linear system being solved. DEPRECATED. use Create

10.4.4

SIDL_C_INLINE_DECL int32_t bHYPRE_CGNR_SetTolerance (bHYPRE_CGNR self, double tolerance, sidl_BaseInterface *_ex)

(Optional) Set the convergence tolerance. DEPRECATED. use SetDoubleParameter

__ 10.4.5 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_CGNR_SetMaxIterations (bHYPRE_CGNR self, int32_t max_iterations, sidl_BaseInterface *_ex)

(Optional) Set maximum number of iterations. DEPRECATED use SetIntParameter

_ 10.4.6 ___

SIDL_C_INLINE_DECL int32_t bHYPRE_CGNR_SetLogging (bHYPRE_CGNR self, int32_t level, sidl_BaseInterface *_ex)

(Optional) Set the *logging level*, specifying the degree of additional informational data to be accumulated. Does nothing by default (level = 0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

10.4.7

(Optional) Set the *print level*, specifying the degree of informational data to be printed either to the screen or to a file. Does nothing by default (level=0). Other levels (if any) are implementation-specific. Must be called before Setup and Apply. DEPRECATED use SetIntParameter

10.4.8

SIDL_C_INLINE_DECL int32_t bHYPRE_CGNR_SetCommunicator (bHYPRE_CGNR self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

10.4.9

SIDL_C_INLINE_DECL void **bHYPRE_CGNR_Destroy** (bHYPRE_CGNR self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

_ 10.4.10 __

RMI connector function for the class. (no addref)

11 Other

11		
Othe	er	
Names 11.1	MPI Communicator	241
11.:	1	
MPI	Communicator	
Names		
11.1.1	struct bHYPRE_MPICommunicator_object Symbol "bHYPRE	243
	_ex Constructor function for the class	
	bHYPRE_MPICommunicator bHYPRE_MPICommunicatorcreateRemote (const char * url,	
	RMI constructor function for the class	
	bHYPRE_MPICommunicator bHYPRE_MPICommunicatorwrapObj (void * data,	
	$Wraps$ up the private data struct pointer (struct $bHYPRE_MPICommunicator_data$) passed in rather than running the constructor	
11.1.2	bHYPRE_MPICommunicator bHYPRE_MPICommunicatorconnect (const char *,	
	RMI connector function for the class	243
	bHYPRE_MPICommunicator bHYPRE_MPICommunicator_CreateC (void* mpi_comm,	
	sidl_BaseInterface *_ex) Create an MPICommunicator object from C code	
	bHYPRE_MPICommunicator bHYPRE_MPICommunicator_CreateF (void* mpi_comm, sidl_BaseInterface *_ex)	
	$SIGL_{f BaseInterface}$ "_ex) Create an MPICommunicator object from Fortran code	
	bHYPRE_MPICommunicator	

11 Other

	$\mathbf{bHYPRE_MPICommunicator_Create_MPICommWorld} \ (\\ \mathbf{sidl_BaseInterface} \\ \\ \bullet \\ \mathbf{bHYPRE_MPICommunicator_Create_MPICommWorld} \ (\\ \mathbf{sidl_BaseInterface} \\ \bullet \\ \mathbf{bHYPRE_MPICommWorld} \ (\\ \mathbf{bHYPRE_MPICOMMWorld} \ ($	
	*_ex) Create an MPICommunicator object which represents MPI_Comm_World	
11.1.3	SIDL_C_INLINE_DECL void bHYPRE_MPICommunicator_Destroy (bHYPRE_MPICommunicator self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	243
	_ex Cast method for interface and class type conversions	
	void^*	
	bHYPRE_MPICommunicator_cast2 (void* obj, const char* type, sidl_BaseInterface *_ex)	
	String cast method for interface and class type conversions	
	SIDL_C_INLINE_DECL void bHYPRE_MPICommunicator_exec (bHYPRE_MPICommunicator self,	
	Select and execute a method by name	
	SIDL_C_INLINE_DECL_char* bHYPRE_MPICommunicatorgetURL (bHYPRE_MPICommunicator self, sidl_BaseInterface *_ex) Get the URL of the Implementation of this object (for RMI)	
	SIDL_C_INLINE_DECL_void	
	bHYPRE_MPICommunicator_raddRef (bHYPRE_MPICommunicator self, sidl_BaseInterface *_ex)	
	On a remote object, addrefs the remote instance	
	SIDL_C_INLINE_DECL sidl_bool bHYPRE_MPICommunicatorisRemote (bHYPRE_MPICommunicator self, sidl_BaseInterface *_ex)	
	TRUE if this object is remote, false if local	
	sidl_bool bHYPRE_MPICommunicatorisLocal (bHYPRE_MPICommunicator self, sidl_BaseInterface *_ex)	
	TRUE if this object is remote, false if local	
	**_ex	
	Cast method for interface and class type conversions	
11.1.4	**_ex RMI connector function for the class	243

11 Other

_ 11.1.1 _

struct bHYPRE_MPICommunicator_object

Symbol "bHYPRE.MPICommunicator" (version 1.0.0)

MPICommunicator class - two general Create functions: use CreateC if called from C code, CreateF if called from Fortran code. - Create_MPICommWorld will create a MPICommunicator to represent MPI_Comm_World, and can be called from any language.

11.1.2

bHYPRE_MPICommunicator bHYPRE_MPICommunicator_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

11.1.3

SIDL_C_INLINE_DECL void **bHYPRE_MPICommunicator_Destroy** (bHYPRE_MPICommunicator self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

11.1.4

struct bHYPRE_MPICommunicator_object* bHYPRE_MPICommunicator_connectI const char * url sidl_bool ar struct sidl_BaseInterface_object **-ex

RMI connector function for the class. (no addref)

12 Struct Grid, etc. Names 12.1 Struct Grid 244 12.2 Struct Stencil 248 Struct Grid Names 12.1.1 $struct\ bHYPRE_StructGrid_object$ Symbol "bHYPRE 246 $_{\mathbf{ex}}$ Constructor function for the class bHYPRE_StructGrid bHYPRE_StructGrid__createRemote (const char * url, sidl_BaseInterface *_ex) RMI constructor function for the class bHYPRE_StructGrid bHYPRE_StructGrid__wrapObj (void * data, sidl_BaseInterface *_ex) $Wraps\ up\ the\ private\ data\ struct\ pointer\ (struct\ bHYPRE_StructGrid__data)$ passed in rather than running the constructor 12.1.2 bHYPRE_StructGrid **bHYPRE_StructGrid__connect** (const char *, sidl_BaseInterface *_ex) RMI connector function for the class 246 bHYPRE_StructGrid bHYPRE_StructGrid_Create (bHYPRE_MPICommunicator mpi_comm, int32_t dim, sidl_BaseInterface *_ex) This function is the preferred way to create a Struct Grid 12.1.3 SIDL_C_INLINE_DECL int32_t bHYPRE_StructGrid_SetCommunicator (bHYPRE_StructGrid self, $b HYPRE_MPIC ommunicator$ mpi_comm,

sidl_BaseInterface *_ex)

Set the MPI Communicator

SIDL_C_INLINE_DECL void

12.1.4

246

	bHYPRE_StructGrid_Destroy (bHYPRE_StructGrid self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	247
	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_StructGrid_SetDimension (bHYPRE_StructGrid self, int32_t dim, sidl_BaseInterface *_ex)	
	Method: SetDimension[]	
12.1.5	$\mathrm{int}32$ _t	
	bHYPRE_StructGrid_SetExtents (bHYPRE_StructGrid self, int32_t* ilower, int32_t* iupper, int32_t dim, sidl_BaseInterface *_ex)	
	Define the lower and upper corners of a box of the grid	247
12.1.6	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_StructGrid_SetPeriodic (bHYPRE_StructGrid self, int32_t* periodic, int32_t dim, sidl_BaseInterface *_ex)	
	Set the periodicity for the grid	247
12.1.7	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_StructGrid_SetNumGhost (bHYPRE_StructGrid self,	
	int32_t* num_ghost, int32_t dim2, sidl_BaseInterface *_ex)	
	Set the number of ghost zones, separately on the lower and upper sides for	
	each dimension	248
	SIDL_C_INLINE_DECL_int32_t bHYPRE_StructGrid_Assemble (bHYPRE_StructGrid self,	
	sidl_BaseInterface *_ex)	
	final construction of the object before its use	
	_ex	
	Cast method for interface and class type conversions	
	void*	
	bHYPRE_StructGridcast2 (void* obj, const char* type, sidl_BaseInterface *_ex)	
	String cast method for interface and class type conversions	
	SIDL_C_INLINE_DECL void	
	bHYPRE_StructGridexec (bHYPRE_StructGrid self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs,	
	sidl_BaseInterface *_ex) Select and execute a method by name	
	SIDL_C_INLINE_DECL_char*	
	bHYPRE_StructGridgetURL (bHYPRE_StructGrid self, sidl_BaseInterface *_ex)	
	Get the URL of the Implementation of this object (for RMI)	
	SIDL_C_INLINE_DECL void	
	bHYPRE_StructGridraddRef (bHYPRE_StructGrid self,	
	sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance	
	SIDL_C_INLINE_DECL_sidl_bool	
	SEE ELC EL TELL TELL DE CHALLOUGE	

bHYPRE_StructGrid_isRemote (bHYPRE_StructGrid self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

sidl_bool

 $\mathbf{bHYPRE_StructGrid__isLocal} \; (\; \; \mathbf{bHYPRE_StructGrid} \; \mathbf{self},$

sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

 $**_{-}ex$

Cast method for interface and class type conversions

12.1.8 **_**ex**

12.1.1

struct bHYPRE_StructGrid_object

Symbol "bHYPRE.StructGrid" (version 1.0.0)

Define a structured grid class.

_ 12.1.2 _

bHYPRE_StructGrid bHYPRE_StructGrid__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

_ 12.1.3 __

SIDL_C_INLINE_DECL int32_t
bHYPRE_StructGrid_SetCommunicator (bHYPRE_StructGrid self,
bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, use Create:

SIDL_C_INLINE_DECL_void $\bf bHYPRE_StructGrid_Destroy$ (<code>bHYPRE_StructGrid</code> self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

12.1.5

int32_t bHYPRE_StructGrid_SetExtents (bHYPRE_StructGrid self, int32_t* ilower, int32_t* iupper, int32_t dim, sidl_BaseInterface *_ex)

Define the lower and upper corners of a box of the grid. "ilower" and "iupper" are arrays of size "dim", the number of spatial dimensions.

12.1.6

SIDL_C_INLINE_DECL int32_t bHYPRE_StructGrid_SetPeriodic (bHYPRE_StructGrid self, int32_t* periodic, int32_t dim, sidl_BaseInterface *_ex)

Set the periodicity for the grid. Default is no periodicity.

The argument periodic is an dim-dimensional integer array that contains the periodicity for each dimension. A zero value for a dimension means non-periodic, while a nonzero value means periodic and contains the actual period. For example, periodicity in the first and third dimensions for a 10x11x12 grid is indicated by the array [10,0,12].

NOTE: Some of the solvers in hypre have power-of-two restrictions on the size of the periodic dimensions.

SIDL_C_INLINE_DECL int32_t bHYPRE_StructGrid_SetNumGhost (bHYPRE_StructGrid self, int32_t* num_ghost, int32_t dim2, sidl_BaseInterface *_ex)

Set the number of ghost zones, separately on the lower and upper sides for each dimension. "num_ghost" is an array of size "dim2", twice the number of dimensions.

__ 12.1.8 ____

struct bHYPRE_StructGrid_object* bHYPRE_StructGrid_connectI const char * url sidl_bool ar struct sidl_BaseInterface_object **_ex

RMI connector function for the class. (no addref)

12.2

Struct Stencil

Names 12.2.1 struct bHYPRE_StructStencil__object Symbol "bHYPRE 250 $_{\mathbf{ex}}$ Constructor function for the class bHYPRE_StructStencil bHYPRE_StructStencil__createRemote (const char * url, sidl_BaseInterface *_ex) RMI constructor function for the class bHYPRE_StructStencil bHYPRE_StructStencil__wrapObj (void * data, sidl_BaseInterface *_ex) theprivatedatastructbHYPRE_StructStencil_data) passed in rather than running the constructor $bHYPRE_StructStencil$ 12.2.2 **bHYPRE_StructStencil__connect** (const char *, sidl_BaseInterface *_ex) RMI connector function for the class 250 bHYPRE_StructStencil 12.2.3

	bHYPRE_StructStencil_Create (int32_t ndim, int32_t size, sidl_BaseInterface *_ex)	
	This function is the preferred way to create a Struct Stencil	250
12.2.4	SIDL_C_INLINE_DECL void bHYPRE_StructStencil_Destroy (bHYPRE_StructStencil self,	
	sidl_BaseInterface *_ex) The Destroy function doesn't necessarily destroy anything	251
12.2.5	SIDL_C_INLINE_DECL int32_t	_01
	bHYPRE_StructStencil_SetDimension (bHYPRE_StructStencil self, int32_t dim, sidl_BaseInterface *_ex)	
	Set the number of dimensions	251
12.2.6	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_StructStencil_SetSize (bHYPRE_StructStencil self, int32_t size, sidl_BaseInterface *_ex)	
	Set the number of stencil entries	251
12.2.7	SIDL_C_INLINE_DECL int32_t bHYPRE_StructStencil_SetElement (bHYPRE_StructStencil self,	
	Set a stencil element	251
	_ex Cast method for interface and class type conversions	
	void^*	
	bHYPRE_StructStencilcast2 (void* obj, const char* type, sidl_BaseInterface *_ex) String cast method for interface and class type conversions	
	SIDL_C_INLINE_DECL void bHYPRE_StructStencil_exec (bHYPRE_StructStencil self, const char* methodName,	
	sidl_rmi_Call inArgs,	
	sidl_rmi_Return outArgs,	
	sidl_BaseInterface *_ex) Select and execute a method by name	
	SIDL_C_INLINE_DECL_char*	
	$b HYPRE_StructStencil__getURL \ (\ bHYPRE_StructStencil \ self, \\ sidl_BaseInterface \ *_ex)$	
	Get the URL of the Implementation of this object (for RMI)	
	SIDL_C_INLINE_DECL_void bHYPRE_StructStencilraddRef (bHYPRE_StructStencil self, sidl_BaseInterface *_ex)	
	On a remote object, addrefs the remote instance	
	SIDL_C_INLINE_DECL sidl_bool	
	bHYPRE_StructStencilisRemote (bHYPRE_StructStencil self, sidl_BaseInterface *_ex)	
	TRUE if this object is remote, false if local	
	sidl_bool	

bHYPRE_StructStencil__isLocal (bHYPRE_StructStencil self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

**_ex

Cast method for interface and class type conversions

12.2.8 **_**e**x

_ 12.2.1 ____

struct bHYPRE_StructStencil_object

Symbol "bHYPRE.StructStencil" (version 1.0.0)

Define a structured stencil for a structured problem description. More than one implementation is not envisioned, thus the decision has been made to make this a class rather than an interface.

12.2.2

bHYPRE_StructStencil bHYPRE_StructStencil__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

12.2.3

bHYPRE_StructStencil bHYPRE_StructStencil_Create (int32_t ndim, int32_t size, sidl_BaseInterface *_ex)

This function is the preferred way to create a Struct Stencil. You provide the number of spatial dimensions and the number of stencil entries.

12.2.4

SIDL_C_INLINE_DECL void bHYPRE_StructStencil_Destroy (bHYPRE_StructStencil self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

12.2.5

SIDL_C_INLINE_DECL int32_t bHYPRE_StructStencil_SetDimension (bHYPRE_StructStencil self, int32_t dim, sidl_BaseInterface *_ex)

Set the number of dimensions. DEPRECATED, use StructStencilCreate

12.2.6

SIDL_C_INLINE_DECL int32_t bHYPRE_StructStencil_SetSize (bHYPRE_StructStencil self, int32_t size, sidl_BaseInterface *_ex)

Set the number of stencil entries. DEPRECATED, use StructStencilCreate

___ 12.2.7 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_StructStencil_SetElement (bHYPRE_StructStencil self, int32_t index, int32_t* offset, int32_t dim, sidl_BaseInterface *_ex)

Set a stencil element. Specify the stencil index, and an array of offsets. "offset" is an array of length "dim", the number of spatial dimensions.

1228

struct bHYPRE_StructStencil_object* bHYPRE_StructStencil_connectI const char * url sidl_bool ar struct sidl_BaseInterface_object **_ex

RMI connector function for the class. (no addref)

__ 13

Semi-Structured Grid, etc.

Names		
13.1	Semi-Structured Graph	056
13.2	Semi-Structured Grid	253
13.3	Semi-Structured Stencil	258 262
13.4	Semi-Structured Variable	265
		200

_ 13.1 _

${\bf Semi\text{-}Structured\ Graph}$

Names		
13.1.1	struct bHYPRE_SStructGraphobject Symbol "bHYPRE	255
	_ex Constructor function for the class	
	bHYPRE_SStructGraph bHYPRE_SStructGraphcreateRemote (const char * url,	
	bHYPRE_SStructGraph bHYPRE_SStructGraphwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_SStructGraphdata) passed in rather than running the constructor	
13.1.2	bHYPRE_SStructGraph bHYPRE_SStructGraphconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	256
	bHYPRE_SStructGraph bHYPRE_SStructGraph_Create (bHYPRE_MPICommunicator mpi_comm, bHYPRE_SStructGrid grid, sidl_BaseInterface *_ex) This function is the preferred way to create a SStruct Graph	
13.1.3	SIDL_C_INLINE_DECL_int32_t	

	bHYPRE_SStructGraph_SetCommGrid (bHYPRE_SStructGraph self, bHYPRE_MPICommunicator	
	${ m mpi_comm},$	
	bHYPRE_SStructGrid grid,	
	sidl_BaseInterface *_ex)	
	Set the grid and communicator	256
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructGraph_SetStencil (bHYPRE_SStructGraph self,	
	int32_t part, int32_t var,	
	bHYPRE_SStructStencil,	
	sidl_BaseInterface *_ex)	
	Set the stencil for a variable on a structured part of the grid	
13.1.4	${ m int}32$ _t	
10.1.4	bHYPRE_SStructGraph_AddEntries (bHYPRE_SStructGraph self,	
	int32_t part, int32_t* index,	
	int32_t dim, int32_t var,	
	int32_t to_part, int32_t* to_index,	
	int32_t to_var,	
	sidl_BaseInterface *_ex)	
	Add a non-stencil graph entry at a particular index	256
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructGraph_SetObjectType (bHYPRE_SStructGraph self,	
	$int32$ _t type,	
	sidl_BaseInterface *_ex)	
	$Method:\ SetObjectType[]$	
13.1.5	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructGraph_SetCommunicator (bHYPRE_SStructGraph self, bHYPRE_MPICommunicator	
	mpi_comm,	
	sidl_BaseInterface *_ex)	
	Set the MPI Communicator	256
13.1.6	SIDL_C_INLINE_DECL void bHYPRE_SStructGraph_Destroy (bHYPRE_SStructGraph self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	257
		201
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructGraph_Initialize (bHYPRE_SStructGraph self, sidl_BaseInterface *_ex)	
	Prepare an object for setting coefficient values, whether for the first time or subsequently	
13.1.7	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructGraph_Assemble (bHYPRE_SStructGraph self,	
	sidl_BaseInterface *_ex)	
	Finalize the construction of an object before using, either for the first time	
	or on subsequent uses	257
	_ex	
	Cast method for interface and class type conversions	
	void^*	
	1010	

bHYPRE_SStructGraph__cast2 (void* obj, const char* type, sidl_BaseInterface *_ex) String cast method for interface and class type conversions SIDL_C_INLINE_DECL_void bHYPRE_SStructGraph__exec (bHYPRE_SStructGraph self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex) Select and execute a method by name SIDL_C_INLINE_DECL char* bHYPRE_SStructGraph__getURL (bHYPRE_SStructGraph self, sidl_BaseInterface *_ex) Get the URL of the Implementation of this object (for RMI) SIDL_C_INLINE_DECL void bHYPRE_SStructGraph_raddRef (bHYPRE_SStructGraph self, sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance SIDL_C_INLINE_DECL sidl_bool bHYPRE_SStructGraph__isRemote (bHYPRE_SStructGraph self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local $sidl_bool$ bHYPRE_SStructGraph__isLocal (bHYPRE_SStructGraph self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local **_ex Cast method for interface and class type conversions

13.1.8 **_ex

RMI connector function for the class

13.1.1

struct bHYPRE_SStructGraph_object

Symbol "bHYPRE.SStructGraph" (version 1.0.0)

The semi-structured grid graph class.

257

_ 13.1.2 _

bHYPRE_SStructGraph
bHYPRE_SStructGraph__connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

__ 13.1.3 _____

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructGraph_SetCommGrid (bHYPRE_SStructGraph self, bHYPRE_MPICommunicator mpi_comm, bHYPRE_SStructGrid grid, sidl_BaseInterface *_ex)

Set the grid and communicator. DEPRECATED, use Create:

13.1.4

int32_t bHYPRE_SStructGraph_AddEntries (bHYPRE_SStructGraph self, int32_t part, int32_t* index, int32_t dim, int32_t var, int32_t to_part, int32_t* to_index, int32_t to_var, sidl_BaseInterface *_ex)

Add a non-stencil graph entry at a particular index. This graph entry is appended to the existing graph entries, and is referenced as such.

NOTE: Users are required to set graph entries on all processes that own the associated variables. This means that some data will be multiply defined.

_ 13.1.5 _

SIDL_C_INLINE_DECL int32_t
bHYPRE_SStructGraph_SetCommunicator (bHYPRE_SStructGraph self,
bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)

Set the MPI Communicator. DEPRECATED, Use Create()

___ 13.1.6 ____

SIDL_C_INLINE_DECL void bHYPRE_SStructGraph_Destroy (bHYPRE_SStructGraph self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

13.1.7

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructGraph_Assemble (bHYPRE_SStructGraph self, sidl_BaseInterface *_ex)

Finalize the construction of an object before using, either for the first time or on subsequent uses. Initialize and Assemble always appear in a matched set, with Initialize preceding Assemble. Values can only be set in between a call to Initialize and Assemble.

13.1.8

struct bHYPRE_SStructGraph__object* bHYPRE_SStructGraph__connectI const char * url sidl_bool ar struct sidl_BaseInterface__object **_ex

RMI connector function for the class. (no addref)

_ 13.2 _

Semi-Structured Grid

Names		
13.2.1	struct bHYPRE_SStructGridobject Symbol "bHYPRE	260
	_ex Constructor function for the class	
	bHYPRE_SStructGrid	
	bHYPRE_SStructGridcreateRemote (const char * url,	
	$sidl_BaseInterface *_ex)$ RMI constructor function for the class	
	bHYPRE_SStructGrid	
	bHYPRE_SStructGridwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_SStructGriddata) passed in rather than running the constructor	
13.2.2	bHYPRE_SStructGrid bHYPRE_SStructGridconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	260
	bHYPRE_SStructGrid bHYPRE_MPICommunicator mpi_comm, int32_t ndim, int32_t nparts, sidl_BaseInterface *_ex) This function is the preferred way to create a SStruct Grid	
	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_SStructGrid_SetNumDimParts (bHYPRE_SStructGrid self, int32_t ndim, int32_t nparts, sidl_BaseInterface *_ex)	
	$Method: \ SetNumDimParts[]$	
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructGrid_SetCommunicator (bHYPRE_SStructGrid self, bHYPRE_MPICommunicator mpi_comm, sidl_BaseInterface *_ex)	
	Method: SetCommunicator[]	
13.2.3	SIDL_C_INLINE_DECL_void bHYPRE_SStructGrid_Destroy (bHYPRE_SStructGrid self,	
	The Destroy function doesn't necessarily destroy anything	261
	int32_t bHYPRE_SStructGrid_SetExtents (bHYPRE_SStructGrid self,	
	Set the extents for a box on a structured part of the grid	
13.2.4	SIDL_C_INLINE_DECL int32_t	

	bHYPRE_SStructGrid_SetVariable (bHYPRE_SStructGrid self,	
	int32_t part, int32_t var,	
	$int32_{-t}$ nvars,	
	enum bHYPRE_SStructVariable_ \perp enum	
	vartype, sidl_BaseInterface *_ex)	
	Describe the variables that live on a structured part of the grid	261
13.2.5	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructGrid_AddVariable (bHYPRE_SStructGrid self,	
	int32_t part, int32_t* index,	
	$int32_t dim$, $int32_t var$,	
	enum bHYPRE_SStructVariableenum	
	vartype, sidl_BaseInterface *_ex)	
	Describe additional variables that live at a particular index	261
13.2.6	$\mathrm{int}32$ _t	
	bHYPRE_SStructGrid_SetNeighborBox (bHYPRE_SStructGrid self,	
	int32_t part, int32_t* ilower,	
	$int 32t^*$ iupper,	
	int32_t nbor_part,	
	$int32_{t}$ nbor_ilower,	
	$int32_{-}t^*$ nbor_iupper,	
	int32_t* index_map, int32_t dim,	
	sidl_BaseInterface *_ex)	
	Describe how regions just outside of a part relate to other parts	261
13.2.7	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_SStructGrid_AddUnstructuredPart (bHYPRE_SStructGrid self,	
	$int32_{-}t$ ilower,	
	$int32_{-}t$ iupper,	
	sidl_BaseInterface *_ex)	
	Add an unstructured part to the grid	262
	SIDL_C_INLINE_DECL int32_t	
	bHYPRE_SStructGrid_SetPeriodic (bHYPRE_SStructGrid self,	
	$int32_{t}$ part, $int32_{t}$ * periodic,	
	int32_t dim, sidl_BaseInterface *_ex)	
	(Optional) Set periodic for a particular part	
	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_SStructGrid_SetNumGhost (bHYPRE_SStructGrid self,	
	int32_t* num_ghost, int32_t dim2,	
	sidl_BaseInterface *_ex)	
	Setting ghost in the sgrids	
	SIDL_C_INLINE_DECL_int32_t	
	bHYPRE_SStructGrid_Assemble (bHYPRE_SStructGrid self,	
	sidl_BaseInterface *_ex) final construction of the object before its use	
	jinai construction of the object before its use	
	_ex	
	Cast method for interface and class type conversions	
	void^*	
	bHYPRE_SStructGridcast2 (void* obj, const char* type,	
	sidl_BaseInterface *_ex)	
	String cast method for interface and class type conversions	
	SIDL_C_INLINE_DECL_void	

bHYPRE_SStructGrid_exec (bHYPRE_SStructGrid self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex) Select and execute a method by name SIDL_C_INLINE_DECL char* bHYPRE_SStructGrid__getURL (bHYPRE_SStructGrid self, sidl_BaseInterface *_ex) Get the URL of the Implementation of this object (for RMI) SIDL_C_INLINE_DECL void bHYPRE_SStructGrid_raddRef (bHYPRE_SStructGrid self, sidl_BaseInterface *_ex) On a remote object, addrefs the remote instance SIDL_C_INLINE_DECL sidl_bool bHYPRE_SStructGrid_isRemote (bHYPRE_SStructGrid self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local sidl_bool bHYPRE_SStructGrid__isLocal (bHYPRE_SStructGrid self, sidl_BaseInterface *_ex) TRUE if this object is remote, false if local **_ex Cast method for interface and class type conversions **_ex 13.2.8

RMI connector function for the class

13.2.1

struct bHYPRE_SStructGrid_object

Symbol "bHYPRE.SStructGrid" (version 1.0.0)

The semi-structured grid class.

13.2.2

bHYPRE_SStructGrid bHYPRE_SStructGrid_connect (const char *, sidl_BaseInterface *_ex)

RMI connector function for the class.(addrefs)

262

13.2.3

SIDL_C_INLINE_DECL void bHYPRE_SStructGrid_Destroy (bHYPRE_SStructGrid self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

13.2.4

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructGrid_SetVariable (bHYPRE_SStructGrid self, int32_t part, int32_t var, int32_t nvars, enum bHYPRE_SStructVariable_enum vartype, sidl_BaseInterface *_ex)

Describe the variables that live on a structured part of the grid. Input: part number, variable number, total number of variables on that part (needed for memory allocation), variable type.

13.2.5

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructGrid_AddVariable (bHYPRE_SStructGrid self, int32_t part, int32_t* index, int32_t dim, int32_t var, enum bHYPRE_SStructVariable_enum vartype, sidl_BaseInterface *_ex)

Describe additional variables that live at a particular index. These variables are appended to the array of variables set in SetVariables, and are referenced as such.

__ 13.2.6 ___

 $int32_t$

bHYPRE_SStructGrid_SetNeighborBox (bHYPRE_SStructGrid self, int32_t part, int32_t* ilower, int32_t* ilower, int32_t* index_map, int32_t dim, sidl_BaseInterface *_ex)

Describe how regions just outside of a part relate to other parts. This is done a box at a time.

The indexes ilower and iupper map directly to the indexes nbor_ilower and nbor_iupper. Although, it is required that indexes increase from ilower to iupper, indexes may increase and/or decrease from nbor_ilower to nbor_iupper.

The index_map describes the mapping of indexes 0, 1, and 2 on part part to the corresponding indexes on part nbor_part. For example, triple (1, 2, 0) means that indexes 0, 1, and 2 on part part map to indexes 1, 2, and 0 on part nbor_part, respectively.

NOTE: All parts related to each other via this routine must have an identical list of variables and variable types. For example, if part 0 has only two variables on it, a cell centered variable and a node centered variable, and we declare part 1 to be a neighbor of part 0, then part 1 must also have only two variables on it, and they must be of type cell and node.

13.2.7

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructGrid_AddUnstructuredPart (bHYPRE_SStructGrid self, int32_t ilower, int32_t iloper, sidl_BaseInterface *_ex)

Add an unstructured part to the grid. The variables in the unstructured part of the grid are referenced by a global rank between 0 and the total number of unstructured variables minus one. Each process owns some unique consecutive range of variables, defined by ilower and iupper.

NOTE: This is just a placeholder. This part of the interface is not finished.

_ 13.2.8 _

RMI connector function for the class. (no addref)

13.3

Semi-Structured Stencil

Names

13.3.1	struct bHYPRE_SStructStencilobject Symbol "bHYPRE	264
	_ex	
	Constructor function for the class	
	bHYPRE_SStructStencil bHYPRE_SStructStencilcreateRemote (const char * url, sidl_BaseInterface *_ex)	
	RMI constructor function for the class	
	bHYPRE_SStructStencil bHYPRE_SStructStencilwrapObj (void * data, sidl_BaseInterface *_ex) Wraps up the private data struct pointer (struct bHYPRE_SStructStencildata) passed in rather than running the con- structor	
13.3.2	bHYPRE_SStructStencil bHYPRE_SStructStencilconnect (const char *, sidl_BaseInterface *_ex) RMI connector function for the class	264
	bHYPRE_SStructStencil bHYPRE_SStructStencil_Create (int32_t ndim, int32_t size, sidl_BaseInterface *_ex) This function is the preferred way to create a SStruct Stencil	
13.3.3	SIDL_C_INLINE_DECL void bHYPRE_SStructStencil_Destroy (bHYPRE_SStructStencil self, sidl_BaseInterface *_ex)	
	The Destroy function doesn't necessarily destroy anything	265
13.3.4	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructStencil_SetNumDimSize (bHYPRE_SStructStencil self, int32_t ndim, int32_t size, sidl_BaseInterface *_ex) Set the number of spatial dimensions and stencil entries	265
		200
	SIDL_C_INLINE_DECL int32_t bHYPRE_SStructStencil_SetEntry (bHYPRE_SStructStencil self,	
	Set a stencil entry	
	_ex	
	Cast method for interface and class type conversions	
	void* bHYPRE_SStructStencilcast2 (void* obj, const char* type, sidl_BaseInterface *_ex)	
	String cast method for interface and class type conversions	
	SIDL_C_INLINE_DECL void	

bHYPRE_SStructStencil_exec (bHYPRE_SStructStencil self, const char* methodName, sidl_rmi_Call inArgs, sidl_rmi_Return outArgs, sidl_BaseInterface *_ex)

Select and execute a method by name

SIDL_C_INLINE_DECL_char*
bHYPRE_SStructStencil__getURL (bHYPRE_SStructStencil self,

bHYPRE_SStructStencil__getURL (bHYPRE_SStructStencil self. sidl_BaseInterface *_ex)

Get the URL of the Implementation of this object (for RMI)

SIDL_C_INLINE_DECL_void

bHYPRE_SStructStencil__raddRef (bHYPRE_SStructStencil self, sidl_BaseInterface *_ex)

On a remote object, addrefs the remote instance

SIDL_C_INLINE_DECL sidl_bool

bHYPRE_SStructStencil__isRemote (bHYPRE_SStructStencil self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

 $sidl_bool$

bHYPRE_SStructStencil__isLocal (bHYPRE_SStructStencil self, sidl_BaseInterface *_ex)

TRUE if this object is remote, false if local

**_ex

 $Cast\ method\ for\ interface\ and\ class\ type\ conversions$

13.3.5 **_ex

RMI connector function for the class

13.3.1 $_{ extstyle -}$

struct bHYPRE_SStructStencil_object

Symbol "bHYPRE.SStructStencil" (version 1.0.0)

The semi-structured grid stencil class.

 $_{-}$ 13.3.2 $_{-}$

bHYPRE_SStructStencil

bHYPRE_SStructStencil__connect (const char *, sidl_BaseInterface *_ex)

265

RMI connector function for the class.(addrefs)

13.3.3

SIDL_C_INLINE_DECL void bHYPRE_SStructStencil_Destroy (bHYPRE_SStructStencil self, sidl_BaseInterface *_ex)

The Destroy function doesn't necessarily destroy anything. It is just another name for deleteRef. Thus it decrements the object's reference count. The Babel memory management system will destroy the object if the reference count goes to zero.

13.3.4

SIDL_C_INLINE_DECL int32_t bHYPRE_SStructStencil_SetNumDimSize (bHYPRE_SStructStencil self, int32_t ndim, int32_t size, sidl_BaseInterface *_ex)

Set the number of spatial dimensions and stencil entries. DEPRECATED, use Create:

__ 13.3.5 _____

RMI connector function for the class. (no addref)

13.4

Semi-Structured Variable

Names

13.4.1 enum bHYPRE_SStructVariable__enum

Symbol "bHYPRE 266

13.4.1

enum bHYPRE_SStructVariable_enum

Symbol "bHYPRE.SStructVariable" (version 1.0.0)

The SStructVariable enumerated type.

An enumerated type that supports cell centered, node centered, face centered, and edge centered variables. Face centered variables are split into x-face, y-face, and z-face variables, and edge centered variables are split into x-edge, y-edge, and z-edge variables. The edge centered variable types are only used in 3D. In 2D, edge centered variables are handled by the face centered types.

Variables are referenced relative to an abstract (cell centered) index in the following way:

- cell centered variables are aligned with the index;
- node centered variables are aligned with the cell corner at relative index (1/2, 1/2, 1/2);
- x-face, y-face, and z-face centered variables are aligned with the faces at relative indexes (1/2, 0, 0), (0, 1/2, 0), and (0, 0, 1/2), respectively;
- x-edge, y-edge, and z-edge centered variables are aligned with the edges at relative indexes (0, 1/2, 1/2), (1/2, 0, 1/2), and (1/2, 1/2, 0), respectively.

The supported identifiers are:

- HYPRE_SSTRUCT_VARIABLE_CELL
- HYPRE_SSTRUCT_VARIABLE_NODE
- HYPRE_SSTRUCT_VARIABLE_XFACE
- HYPRE_SSTRUCT_VARIABLE_YFACE
- HYPRE_SSTRUCT_VARIABLE_ZFACE
- HYPRE_SSTRUCT_VARIABLE_XEDGE
- HYPRE_SSTRUCT_VARIABLE_YEDGE
- HYPRE_SSTRUCT_VARIABLE_ZEDGE

NOTE: Although variables are referenced relative to a unique abstract cell-centered index, some variables are associated with multiple grid cells. For example, node centered variables in 3D are associated with 8 cells (away from boundaries). Although grid cells are distributed uniquely to different processes, variables may be owned by multiple processes because they may be associated with multiple cells.

Class Graph