## Fast Auxiliary Space Preconditioning 1.3.7 Sep/30/2013

Generated by Doxygen 1.8.5

Mon Sep 30 2013 14:49:54

## **Contents**

1	Intro	eduction Control of the Control of t	1
2	How	to obtain FASP	3
3	Build	ding and Installation	5
4	Deve	elopers	7
5	Doxy	ygen	9
6	Data	Structure Index	11
	6.1	Data Structures	11
7	File	Index	13
	7.1	File List	13
8	Data	Structure Documentation	19
	8.1	AMG_data Struct Reference	19
		8.1.1 Detailed Description	20
	8.2	AMG_data_bsr Struct Reference	20
		8.2.1 Detailed Description	21
	8.3	AMG_param Struct Reference	21
		8.3.1 Detailed Description	23
	8.4	block_BSR Struct Reference	23
		8.4.1 Detailed Description	24
	8.5	block_dCSRmat Struct Reference	24
		8.5.1 Detailed Description	24
	8.6	block_dvector Struct Reference	25
		8.6.1 Detailed Description	25
	8.7	block_iCSRmat Struct Reference	25
		8.7.1 Detailed Description	25

iv CONTENTS

8.8	block_ivector Struct Reference	 26
	8.8.1 Detailed Description	 26
8.9	block_Reservoir Struct Reference	 26
	8.9.1 Detailed Description	 26
8.10	dBSRmat Struct Reference	 27
	8.10.1 Detailed Description	 27
	8.10.2 Field Documentation	 27
	8.10.2.1 JA	 27
	8.10.2.2 val	 28
8.11	dCOOmat Struct Reference	 28
	8.11.1 Detailed Description	 28
8.12	2 dCSRLmat Struct Reference	 29
	8.12.1 Detailed Description	 29
8.13	dCSRmat Struct Reference	 29
	8.13.1 Detailed Description	 30
8.14	ddenmat Struct Reference	 30
	8.14.1 Detailed Description	 30
8.15	5 dSTRmat Struct Reference	 31
	8.15.1 Detailed Description	 31
8.16	dvector Struct Reference	 31
	8.16.1 Detailed Description	 32
8.17	grid2d Struct Reference	 32
	8.17.1 Detailed Description	 32
	8.17.2 Field Documentation	 33
	8.17.2.1 e	 33
	8.17.2.2 edges	 33
	8.17.2.3 ediri	 33
	8.17.2.4 efather	 33
	8.17.2.5 p	 33
	8.17.2.6 pdiri	 33
	8.17.2.7 pfather	 33
	8.17.2.8 s	 33
	8.17.2.9 t	 34
	8.17.2.10 tfather	 34
	8.17.2.11 triangles	 34
	8.17.2.12 vertices	 34
8.18	3 iCOOmat Struct Reference	 34

CONTENTS

	8.18.1	Detailed I	Description	
8.19	iCSRm	at Struct F	Reference	
	8.19.1	Detailed I	Description	
8.20	idenma	at Struct Re	eference	
	8.20.1	Detailed I	Description	
8.21	ILU_da	ıta Struct F	Reference	
	8.21.1	Detailed I	Description	
8.22	ILU_pa	ram Struc	t Reference	
			Description	
8.23			ct Reference	
			Description	
	8.23.2		cumentation	
			AMG_aggressive_level	
			AMG_aggressive_path	
			AMG_amli_degree	
		8.23.2.4	AMG_coarse_dof	
			AMG_coarse_scaling	
			AMG_coarsening_type	
			AMG_cycle_type	
			AMG_ILU_levels	
			AMG_interpolation_type	
			AMG_levels	
			AMG_max_aggregation	
			AMG_max_row_sum	
			AMG_maxit	
			AMG_nl_amli_krylov_type	
			AMG_polynomial_degree	
			AMG_postsmooth_iter	
			AMG_presmooth_iter	
			AMG_relaxation	
			AMG_schwarz_levels	
			AMG_smooth_filter	
			AMG_smooth_order	
			PAMG_smoother	
			AMG_strong_coupled	
			AMG_strong_threshold	
		8.23.2.25	AMG_tentative_smooth	4

vi CONTENTS

		8.23.2.26	AMG_	_tol				 	 	 	 	 	 	. 42
		8.23.2.27	AMG_	_trunca	tion_th	hresh	old	 	 	 	 	 	 	. 42
		8.23.2.28	AMG_	_type				 	 	 	 	 	 	. 42
		8.23.2.29	ILU_d	roptol .				 	 	 	 	 	 	. 42
		8.23.2.30	ILU_lf	fil				 	 	 	 	 	 	. 42
		8.23.2.31	ILU_p	ermtol				 	 	 	 	 	 	. 42
		8.23.2.32	ILU_r	elax .				 	 	 	 	 	 	. 42
		8.23.2.33	ILU_t	ype .				 	 	 	 	 	 	. 42
		8.23.2.34	itsolve	er_max	it			 	 	 	 	 	 	. 42
		8.23.2.35	itsolve	er_tol .				 	 	 	 	 	 	. 43
		8.23.2.36	outpu	t_type				 	 	 	 	 	 	. 43
		8.23.2.37	preco	nd_typ	е			 	 	 	 	 	 	. 43
		8.23.2.38	print_	level				 	 	 	 	 	 	. 43
		8.23.2.39	proble	em_nur	n			 	 	 	 	 	 	. 43
		8.23.2.40	restar	t				 	 	 	 	 	 	. 43
		8.23.2.41	Schwa	arz_ma	axlvl .			 	 	 	 	 	 	. 43
		8.23.2.42	Schwa	arz_mr	nsize			 	 	 	 	 	 	. 43
		8.23.2.43	Schwa	arz_typ	e			 	 	 	 	 	 	. 43
		8.23.2.44	solver	r_type				 	 	 	 	 	 	. 44
		8.23.2.45	stop_	type .				 	 	 	 	 	 	. 44
		8.23.2.46	workd	dir				 	 	 	 	 	 	. 44
8.24	itsolver	_param Str	ruct Re	eferenc	e			 	 	 	 	 	 	. 44
	8.24.1	Detailed D	Descrip	otion				 	 	 	 	 	 	. 44
	8.24.2	Field Docu	ument	ation				 	 	 	 	 	 	. 44
		8.24.2.1	itsolve	er_type				 	 	 	 	 	 	. 44
		8.24.2.2	maxit					 	 	 	 	 	 	. 45
		8.24.2.3	preco	nd_typ	е			 	 	 	 	 	 	. 45
		8.24.2.4	print_	level				 	 	 	 	 	 	. 45
		8.24.2.5	restar	t				 	 	 	 	 	 	. 45
		8.24.2.6	stop_	type.				 	 	 	 	 	 	. 45
		8.24.2.7	tol .					 	 	 	 	 	 	. 45
8.25	ivector	Struct Refe	erence					 	 	 	 	 	 	. 45
	8.25.1	Detailed D	Descrip	otion				 	 	 	 	 	 	. 46
8.26	Link St	ruct Refere	nce .					 	 	 	 	 	 	. 46
	8.26.1	Detailed D	Descrip	otion				 	 	 	 	 	 	. 46
8.27	linked_	list Struct R	Refere	nce .				 	 	 	 	 	 	. 46
	8.27.1	Detailed D	Descrip	otion				 	 	 	 	 	 	. 47

CONTENTS vii

8.28	8 mxv_matfree Struct Reference	47
	8.28.1 Detailed Description	47
8.29	9 precond Struct Reference	47
	8.29.1 Detailed Description	48
8.30	0 precond_block_data Struct Reference	48
	8.30.1 Detailed Description	48
	8.30.2 Field Documentation	48
	8.30.2.1 A	48
	8.30.2.2 Aarray	48
	8.30.2.3 Ablock	49
	8.30.2.4 amgparam	49
	8.30.2.5 col_idx	49
	8.30.2.6 r	49
	8.30.2.7 row_idx	
8.31	1 precond_block_reservoir_data Struct Reference	49
	8.31.1 Detailed Description	51
	8.31.2 Field Documentation	51
	8.31.2.1 diag	
	8.31.2.2 diaginv	51
	8.31.2.3 diaginvS	51
	8.31.2.4 order	51
	8.31.2.5 perf_idx	
	8.31.2.6 pivot	
	8.31.2.7 pivotS	
	8.31.2.8 PP	52
	8.31.2.9 r	52
	8.31.2.10 RR	
	8.31.2.11 scaled	52
	8.31.2.12 SS	52
	8.31.2.13 w	52
	8.31.2.14 WW	52
8.32	2 precond_data Struct Reference	52
	8.32.1 Detailed Description	54
8.33	3 precond_data_bsr Struct Reference	54
	8.33.1 Detailed Description	55
8.34	4 precond_data_str Struct Reference	55
	8.34.1 Detailed Description	57

viii CONTENTS

	8.35	precon	d_diagbsr Struct Reference	57
		8.35.1	Detailed Description	57
	8.36	precon	d_diagstr Struct Reference	57
		8.36.1	Detailed Description	58
	8.37	precon	d_FASP_blkoil_data Struct Reference	58
		8.37.1	Detailed Description	59
		8.37.2	Field Documentation	59
			8.37.2.1 A	59
			8.37.2.2 diaginv	30
			8.37.2.3 diaginv_noscale	30
			8.37.2.4 diaginv_S	30
			8.37.2.5 maxit	30
			8.37.2.6 mgl_data	30
			8.37.2.7 neigh	30
			8.37.2.8 order	30
			8.37.2.9 perf_idx	30
			8.37.2.10 perf_neigh	30
			8.37.2.11 pivot	31
			8.37.2.12 pivot_S	31
			8.37.2.13 PP	31
			8.37.2.14 r	31
			8.37.2.15 restart	31
			8.37.2.16 RR	31
			8.37.2.17 scaled	31
			8.37.2.18 SS	31
			8.37.2.19 tol	32
			8.37.2.20 w	32
			8.37.2.21 WW	32
	8.38	Schwai	z_data Struct Reference	32
		8.38.1	Detailed Description	33
	8.39	Schwai	z_param Struct Reference	33
		8.39.1	Detailed Description	33
9	Eilo !	Doouma	entation	65
3	9.1		File Reference	
	J. I	amg.c	Detailed Description	
		_	Function Documentation	
		9.1.2	rundion documentation	כנ

CONTENTS ix

		9.1.2.1 fasp_solver_amg
9.2	amg_s	etup_aggregation_bsr.inl File Reference
	9.2.1	Detailed Description
9.3	amg_s	etup_aggregation_csr.inl File Reference
	9.3.1	Detailed Description
9.4	amg_s	etup_cr.c File Reference
	9.4.1	Detailed Description
	9.4.2	Function Documentation
		9.4.2.1 fasp_amg_setup_cr
9.5	amg_s	etup_rs.c File Reference
	9.5.1	Detailed Description
	9.5.2	Function Documentation
		9.5.2.1 fasp_amg_setup_rs
		9.5.2.2 fasp_amg_setup_rs_omp
9.6	amg_s	etup_sa.c File Reference
	9.6.1	Detailed Description
	9.6.2	Function Documentation
		9.6.2.1 fasp_amg_setup_sa
9.7	amg_s	etup_ua.c File Reference
	9.7.1	Detailed Description
	9.7.2	Function Documentation
		9.7.2.1 fasp_amg_setup_ua
		9.7.2.2 fasp_amg_setup_ua_bsr
9.8	amg_s	olve.c File Reference
	9.8.1	Detailed Description
	9.8.2	Function Documentation
		9.8.2.1 fasp_amg_solve
		9.8.2.2 fasp_amg_solve_amli
		9.8.2.3 fasp_amg_solve_nl_amli
		9.8.2.4 fasp_famg_solve
9.9	amlired	cur.c File Reference
	9.9.1	Detailed Description
	9.9.2	Function Documentation
		9.9.2.1 fasp_amg_amli_coef
		9.9.2.2 fasp_solver_amli
		9.9.2.3 fasp_solver_nl_amli
		9.9.2.4 fasp_solver_nl_amli_bsr

CONTENTS

9.10	array.c	File Refer	ence				 	 	 	 	 	 	77
	9.10.1	Detailed	Description				 	 	 	 	 	 	78
	9.10.2	Function	Documenta	ition .			 	 	 	 	 	 	78
		9.10.2.1	fasp_array	_cp .			 	 	 	 	 	 	78
		9.10.2.2	fasp_array	_cp_nc	<b>3</b>		 	 	 	 	 	 	78
		9.10.2.3	fasp_array	_cp_nc	<b>:5</b>		 	 	 	 	 	 	79
		9.10.2.4	fasp_array	_cp_nc	7		 	 	 	 	 	 	79
		9.10.2.5	fasp_array	_null .			 	 	 	 	 	 	79
		9.10.2.6	fasp_array	_set .			 	 	 	 	 	 	80
		9.10.2.7	fasp_iarray	y_cp .			 	 	 	 	 	 	80
		9.10.2.8	fasp_iarray	y_set .			 	 	 	 	 	 	81
9.11	blas_ar	ray.c File	Reference				 	 	 	 	 	 	81
	9.11.1	Detailed	Description				 	 	 	 	 	 	82
	9.11.2	Function	Documenta	ition .			 	 	 	 	 	 	82
		9.11.2.1	fasp_blas_	_array_a	ax		 	 	 	 	 	 	82
		9.11.2.2	fasp_blas_	_array_a	axpby		 	 	 	 	 	 	82
		9.11.2.3	fasp_blas_	_array_a	axpy .		 	 	 	 	 	 	83
		9.11.2.4	fasp_blas_	_array_a	axpyz .		 	 	 	 	 	 	83
		9.11.2.5	fasp_blas_	_array_c	dotprod	l	 	 	 	 	 	 	84
		9.11.2.6	fasp_blas_	_array_r	norm1		 	 	 	 	 	 	84
		9.11.2.7	fasp_blas_	_array_r	norm2		 	 	 	 	 	 	85
		9.11.2.8	fasp_blas_	_array_r	norminf	f	 	 	 	 	 	 	85
9.12	blas_bo	csr.c File F	Reference				 	 	 	 	 	 	86
	9.12.1	Detailed	Description				 	 	 	 	 	 	86
	9.12.2	Function	Documenta	ıtion .			 	 	 	 	 	 	87
		9.12.2.1	fasp_blas_	_bdbsr_	аАхру		 	 	 	 	 	 	87
		9.12.2.2	fasp_blas_	_bdbsr_	mxv .		 	 	 	 	 	 	88
		9.12.2.3	fasp_blas_	_bdcsr_	аАхру		 	 	 	 	 	 	88
		9.12.2.4	fasp_blas_	_bdcsr_	mxv .		 	 	 	 	 	 	89
9.13	blas_bs	sr.c File Re	eference .				 	 	 	 	 	 	89
	9.13.1	Detailed	Description				 	 	 	 	 	 	89
	9.13.2	Function	Documenta	ıtion .			 	 	 	 	 	 	90
		9.13.2.1	fasp_blas_	_dbsr_a	Axpby		 	 	 	 	 	 	90
		9.13.2.2	fasp_blas_	_dbsr_a	Ахру .		 	 	 	 	 	 	91
		9.13.2.3	fasp_blas_	_dbsr_m	nxv		 	 	 	 	 	 	92
		9.13.2.4	fasp_blas_	_dbsr_ra	ар		 	 	 	 	 	 	93
		9.13.2.5	fasp_blas_	_dbsr_ra	ар1		 	 	 	 	 	 	93

CONTENTS xi

9.14	blas_cs	sr.c File Re	eference .				 	 	 	 		 	94
	9.14.1	Detailed I	Description				 	 	 	 		 	95
	9.14.2	Function	Documenta	ation			 	 	 	 		 	95
		9.14.2.1	fasp_blas_	_dcsr_	aAxpy		 	 	 	 		 	95
		9.14.2.2	fasp_blas_	_dcsr_	aAxpy_	_agg .	 	 	 	 		 	96
		9.14.2.3	fasp_blas_	_dcsr_	add .		 	 	 	 		 	96
		9.14.2.4	fasp_blas_	_dcsr_	axm .		 	 	 	 		 	96
		9.14.2.5	fasp_blas_	_dcsr_	mxm		 	 	 	 		 	97
		9.14.2.6	fasp_blas_	_dcsr_	mxv .		 	 	 	 		 	97
		9.14.2.7	fasp_blas_	_dcsr_	mxv_a	gg	 	 	 	 		 	98
		9.14.2.8	fasp_blas_	_dcsr_	ptap .		 	 	 	 		 	98
		9.14.2.9	fasp_blas_	_dcsr_	rap .		 	 	 	 		 	99
		9.14.2.10	fasp_blas_	_dcsr_	rap4 .		 	 	 	 		 	99
		9.14.2.11	fasp_blas_	_dcsr_	rap_ag	g	 	 	 	 		 	100
		9.14.2.12	fasp_blas_	_dcsr_	rap_ag	g1	 	 	 	 		 	100
		9.14.2.13	fasp_blas_	_dcsr_	vmv .		 	 	 	 		 	101
9.15	blas_cs	srl.c File R	eference .				 	 	 	 		 	101
	9.15.1	Detailed I	Description				 	 	 	 		 	102
	9.15.2	Function	Documenta	ation			 	 	 	 		 	102
		9.15.2.1	fasp_blas_	_dcsrl_	_mxv .		 	 	 	 		 	102
9.16	blas_sr	mat.c File I	Reference				 	 	 	 		 	102
	9.16.1	Detailed I	Description				 	 	 	 		 	104
	9.16.2	Function	Documenta	ation			 	 	 	 		 	104
		9.16.2.1	fasp_blas_	_array_	_axpy_	nc2	 	 	 	 		 	104
		9.16.2.2	fasp_blas_	_array_	_axpy_	nc3	 	 	 	 		 	104
		9.16.2.3	fasp_blas_	_array_	_axpy_	nc5	 	 	 	 		 	105
		9.16.2.4	fasp_blas_	_array_	_axpy_	nc7	 	 	 	 		 	105
		9.16.2.5	fasp_blas_	_array_	_axpyz_	_nc2 .	 	 	 	 		 	105
		9.16.2.6	fasp_blas_	_array_	_axpyz	_nc3 .	 	 	 	 		 	106
		9.16.2.7	fasp_blas_	_array_	_axpyz <sub>-</sub>	_nc5 .	 	 	 	 		 	106
		9.16.2.8	fasp_blas_	_array_	_axpyz <sub>-</sub>	_nc7 .	 	 	 	 		 	107
		9.16.2.9	fasp_blas_	_smat_	_aAxpb	y	 	 	 	 		 	107
		9.16.2.10	fasp_blas_	_smat_	_mul .		 	 	 	 		 	108
		9.16.2.11	fasp_blas_	_smat_	_mul_n	c2	 	 	 	 		 	108
		9.16.2.12	fasp_blas_	_smat_	_mul_n	c3	 	 	 	 		 	109
		9.16.2.13	fasp_blas_	_smat_	_mul_n	c5	 	 	 	 		 	109
		9.16.2.14	fasp_blas_	_smat_	_mul_n	c7	 	 	 	 		 	109

xii CONTENTS

9.16.2.15 tasp_blas_smat_mxv	110
9.16.2.16 fasp_blas_smat_mxv_nc2	110
9.16.2.17 fasp_blas_smat_mxv_nc3	111
9.16.2.18 fasp_blas_smat_mxv_nc5	112
9.16.2.19 fasp_blas_smat_mxv_nc7	112
9.16.2.20 fasp_blas_smat_ymAx	113
9.16.2.21 fasp_blas_smat_ymAx_nc2	114
9.16.2.22 fasp_blas_smat_ymAx_nc3	114
9.16.2.23 fasp_blas_smat_ymAx_nc5	115
9.16.2.24 fasp_blas_smat_ymAx_nc7	115
9.16.2.25 fasp_blas_smat_ymAx_ns	116
9.16.2.26 fasp_blas_smat_ymAx_ns2	116
9.16.2.27 fasp_blas_smat_ymAx_ns3	117
9.16.2.28 fasp_blas_smat_ymAx_ns5	117
9.16.2.29 fasp_blas_smat_ymAx_ns7	118
9.16.2.30 fasp_blas_smat_ypAx	118
9.16.2.31 fasp_blas_smat_ypAx_nc2	119
9.16.2.32 fasp_blas_smat_ypAx_nc3	119
9.16.2.33 fasp_blas_smat_ypAx_nc5	120
9.16.2.34 fasp_blas_smat_ypAx_nc7	121
9.17 blas_str.c File Reference	121
9.17.1 Detailed Description	122
9.17.2 Function Documentation	122
9.17.2.1 fasp_blas_dstr_aAxpy	122
9.17.2.2 fasp_blas_dstr_mxv	122
9.17.2.3 fasp_dstr_diagscale	122
9.18 blas_vec.c File Reference	123
9.18.1 Detailed Description	123
9.18.2 Function Documentation	124
9.18.2.1 fasp_blas_dvec_axpy	124
9.18.2.2 fasp_blas_dvec_axpyz	124
9.18.2.3 fasp_blas_dvec_dotprod	124
9.18.2.4 fasp_blas_dvec_norm1	125
9.18.2.5 fasp_blas_dvec_norm2	125
9.18.2.6 fasp_blas_dvec_norminf	126
9.18.2.7 fasp_blas_dvec_relerr	126
9.19 checkmat.c File Reference	127

CONTENTS xiii

9.1	19.1	Detailed Description
9.1	19.2	Function Documentation
		9.19.2.1 fasp_check_dCSRmat
		9.19.2.2 fasp_check_diagdom
		9.19.2.3 fasp_check_diagpos
		9.19.2.4 fasp_check_diagzero
		9.19.2.5 fasp_check_iCSRmat
		9.19.2.6 fasp_check_symm
9.20 co	arsen	ning_cr.c File Reference
9.2	20.1	Detailed Description
9.2	20.2	Function Documentation
		9.20.2.1 fasp_amg_coarsening_cr
9.21 co	arsen	ning_rs.c File Reference
9.2	21.1	Detailed Description
9.2	21.2	Function Documentation
		9.21.2.1 fasp_amg_coarsening_rs
9.22 co	nvert.	.c File Reference
9.2	22.1	Detailed Description
9.2	22.2	Function Documentation
		9.22.2.1 endian_convert_int
		9.22.2.2 endian_convert_real
		9.22.2.3 fasp_aux_bbyteToldouble
		9.22.2.4 fasp_aux_change_endian4
		9.22.2.5 fasp_aux_change_endian8
9.23 do	xyger	n.h File Reference
9.2	23.1	Detailed Description
9.24 eig	gen.c	File Reference
9.2	24.1	Detailed Description
9.2	24.2	Function Documentation
		9.24.2.1 fasp_dcsr_eig
9.25 fac	ctor.f	File Reference
9.2	25.1	Detailed Description
9.26 far	mg.c l	File Reference
9.2	26.1	Detailed Description
9.2	26.2	Function Documentation
		9.26.2.1 fasp_solver_famg
9.27 fas	sp.h F	File Reference

xiv CONTENTS

Detailed Description
Macro Definition Documentation
9.27.2.1FASP_HEADER
9.27.2.2 ABS
9.27.2.3 BIGREAL
9.27.2.4 C2N
9.27.2.5 CHMEM_MODE
9.27.2.6 DEBUG_MODE
9.27.2.7 DIAGONAL_PREF
9.27.2.8 DLMALLOC
9.27.2.9 FASP_GSRB145
9.27.2.10 FASP_USE_ILU
9.27.2.11 GE
9.27.2.12 GT
9.27.2.13 INT
9.27.2.14 ISNAN
9.27.2.15 ISTART
9.27.2.16 LE
9.27.2.17 LONG
9.27.2.18 LS
9.27.2.19 MAX
9.27.2.20 MAX_AMG_LVL
9.27.2.21 MAX_REFINE_LVL
9.27.2.22 MAX_RESTART
9.27.2.23 MAX_STAG
9.27.2.24 MIN
9.27.2.25 N2C
9.27.2.26 NEDMALLOC
9.27.2.27 OPENMP_HOLDS
9.27.2.28 REAL
9.27.2.29 SHORT
9.27.2.30 SMALLREAL
9.27.2.31 STAG_RATIO
Typedef Documentation
9.27.3.1 dCOOmat
9.27.3.2 dCSRLmat
9.27.3.3 dCSRmat

CONTENTS xv

		9.27.3.4	ddenmat	. 148
		9.27.3.5	dSTRmat	. 148
		9.27.3.6	dvector	. 148
		9.27.3.7	grid2d	. 148
		9.27.3.8	iCOOmat	. 149
		9.27.3.9	iCSRmat	. 149
		9.27.3.10	idenmat	. 149
		9.27.3.11	ivector	. 149
		9.27.3.12	LinkList	. 149
		9.27.3.13	ListElement	. 149
		9.27.3.14	pcgrid2d	. 149
		9.27.3.15	pgrid2d	. 149
	9.27.4	Variable [	Documentation	. 149
		9.27.4.1	IMAP	. 149
		9.27.4.2	MAXIMAP	. 149
		9.27.4.3	nx_rb	. 150
		9.27.4.4	ny_rb	. 150
		9.27.4.5	nz_rb	. 150
		9.27.4.6	total_alloc_count	. 150
		9.27.4.7	total_alloc_mem	. 150
9.28	fasp_bl	ock.h File	Reference	. 150
	9.28.1	Detailed I	Description	. 151
	9.28.2	Typedef E	Documentation	. 151
		9.28.2.1	block_BSR	. 151
		9.28.2.2	block_dCSRmat	. 151
		9.28.2.3	block_dvector	. 152
		9.28.2.4	block_iCSRmat	. 152
		9.28.2.5	block_ivector	. 152
		9.28.2.6	block_Reservoir	. 152
		9.28.2.7	dBSRmat	. 152
		9.28.2.8	precond_block_reservoir_data	. 152
9.29	fmgcyc	le.c File R	eference	. 152
	9.29.1	Detailed I	Description	. 152
	9.29.2	Function	Documentation	. 153
		9.29.2.1	fasp_solver_fmgcycle	. 153
9.30	formats	s.c File Ref	ference	. 153
	9.30.1	Detailed I	Description	. 154

xvi CONTENTS

9.30	Function Documentation	154
	9.30.2.1 fasp_format_bdcsr_dcsr	154
	9.30.2.2 fasp_format_dbsr_dcoo	154
	9.30.2.3 fasp_format_dbsr_dcsr	154
	9.30.2.4 fasp_format_dcoo_dcsr	155
	9.30.2.5 fasp_format_dcsr_dbsr	155
	9.30.2.6 fasp_format_dcsr_dcoo	156
	9.30.2.7 fasp_format_dcsrl_dcsr	156
	9.30.2.8 fasp_format_dstr_dbsr	157
	9.30.2.9 fasp_format_dstr_dcsr	157
9.31 give	s.c File Reference	158
9.31	1 Detailed Description	158
9.31	2 Function Documentation	158
	9.31.2.1 fasp_aux_givens	158
9.32 gmg	poisson.c File Reference	159
9.32	1 Detailed Description	159
9.32	2 Function Documentation	159
	9.32.2.1 fasp_poisson_fgmg_1D	159
	9.32.2.2 fasp_poisson_fgmg_2D	160
	9.32.2.3 fasp_poisson_fgmg_3D	160
	9.32.2.4 fasp_poisson_gmg_1D	161
	9.32.2.5 fasp_poisson_gmg_2D	161
	9.32.2.6 fasp_poisson_gmg_3D	162
	9.32.2.7 fasp_poisson_pcg_gmg_1D	162
	9.32.2.8 fasp_poisson_pcg_gmg_2D	
	9.32.2.9 fasp_poisson_pcg_gmg_3D	163
9.33 gmg	util.inl File Reference	164
9.33	1 Detailed Description	164
9.34 grap	ics.c File Reference	164
9.34	1 Detailed Description	165
9.34	Function Documentation	165
	9.34.2.1 fasp_dcsr_plot	165
	9.34.2.2 fasp_grid2d_plot	165
9.35 ilu.f	ile Reference	166
9.35	1 Detailed Description	166
9.36 ilu_s	etup_bsr.c File Reference	166
9.36	1 Detailed Description	166

CONTENTS xvii

	9.36.2	Function Documentation	167		
		9.36.2.1 fasp_ilu_dbsr_setup	167		
9.37	ilu_setu	up_csr.c File Reference	168		
	9.37.1	Detailed Description	168		
	9.37.2	Function Documentation	168		
		9.37.2.1 fasp_ilu_dcsr_setup	168		
9.38	ilu_setu	up_str.c File Reference	169		
	9.38.1	Detailed Description	169		
	9.38.2	Function Documentation	169		
		9.38.2.1 fasp_ilu_dstr_setup0	169		
		9.38.2.2 fasp_ilu_dstr_setup1	170		
9.39	init.c Fi	le Reference	170		
	9.39.1	Detailed Description	171		
	9.39.2	Function Documentation	171		
		9.39.2.1 fasp_amg_data_bsr_create	171		
		9.39.2.2 fasp_amg_data_bsr_free	172		
		9.39.2.3 fasp_amg_data_create	172		
		9.39.2.4 fasp_amg_data_free	172		
		9.39.2.5 fasp_ilu_data_alloc	173		
		9.39.2.6 fasp_ilu_data_free	173		
		9.39.2.7 fasp_ilu_data_null	173		
		9.39.2.8 fasp_precond_null	174		
		9.39.2.9 fasp_schwarz_data_free	174		
9.40	40 input.c File Reference				
	9.40.1	Detailed Description	175		
	9.40.2	Function Documentation	175		
		9.40.2.1 fasp_param_input	175		
9.41	interfac	e_mumps.c File Reference	175		
	9.41.1	Detailed Description	176		
	9.41.2	Function Documentation	176		
		9.41.2.1 fasp_solver_mumps	176		
		9.41.2.2 fasp_solver_mumps_steps	176		
9.42	interfac	e_samg.c File Reference	177		
	9.42.1	Detailed Description	177		
	9.42.2	Function Documentation	177		
		9.42.2.1 dCSRmat2SAMGInput	177		
		9.42.2.2 dvector2SAMGInput	177		

xviii CONTENTS

9.43	interfac	e_superlu.c File Reference
	9.43.1	Detailed Description
	9.43.2	Function Documentation
		9.43.2.1 fasp_solver_superlu
9.44	interfac	e_umfpack.c File Reference
	9.44.1	Detailed Description
	9.44.2	Function Documentation
		9.44.2.1 fasp_solver_umfpack
9.45	interpo	lation.c File Reference
	9.45.1	Detailed Description
	9.45.2	Function Documentation
		9.45.2.1 fasp_amg_interp
		9.45.2.2 fasp_amg_interp1
		9.45.2.3 fasp_amg_interp_trunc
9.46	interpo	lation_em.c File Reference
	9.46.1	Detailed Description
	9.46.2	Function Documentation
		9.46.2.1 fasp_amg_interp_em
9.47	io.c File	Reference
	9.47.1	Detailed Description
	9.47.2	Function Documentation
		9.47.2.1 fasp_dbsr_print
		9.47.2.2 fasp_dbsr_read
		9.47.2.3 fasp_dbsr_write
		9.47.2.4 fasp_dcoo1_read
		9.47.2.5 fasp_dcoo_print
		9.47.2.6 fasp_dcoo_read
		9.47.2.7 fasp_dcoo_write
		9.47.2.8 fasp_dcsr_print
		9.47.2.9 fasp_dcsr_read
		9.47.2.10 fasp_dcsrvec1_read
		9.47.2.11 fasp_dcsrvec1_write
		9.47.2.12 fasp_dcsrvec2_read
		9.47.2.13 fasp_dcsrvec2_write
		9.47.2.14 fasp_dmtx_read
		9.47.2.15 fasp_dmtxsym_read
		9.47.2.16 fasp_dstr_print

CONTENTS xix

		9.47.2.17 fasp_dstr_read
		9.47.2.18 fasp_dstr_write
		9.47.2.19 fasp_dvec_print
		9.47.2.20 fasp_dvec_read
		9.47.2.21 fasp_dvec_write
		9.47.2.22 fasp_dvecind_read
		9.47.2.23 fasp_dvecind_write
		9.47.2.24 fasp_ivec_print
		9.47.2.25 fasp_ivec_read
		9.47.2.26 fasp_ivec_write
		9.47.2.27 fasp_ivecind_read
		9.47.2.28 fasp_matrix_read
		9.47.2.29 fasp_matrix_read_bin
		9.47.2.30 fasp_matrix_write
		9.47.2.31 fasp_vector_read
		9.47.2.32 fasp_vector_write
9.48	itsolver	_bcsr.c File Reference
	9.48.1	Detailed Description
	9.48.2	Function Documentation
		9.48.2.1 fasp_solver_bdcsr_itsolver
		9.48.2.2 fasp_solver_bdcsr_krylov
9.49	itsolver	_bsr.c File Reference
	9.49.1	Detailed Description
	9.49.2	Function Documentation
		9.49.2.1 fasp_set_GS_threads
		9.49.2.2 fasp_solver_dbsr_itsolver
		9.49.2.3 fasp_solver_dbsr_krylov
		9.49.2.4 fasp_solver_dbsr_krylov_amg
		9.49.2.5 fasp_solver_dbsr_krylov_diag
		9.49.2.6 fasp_solver_dbsr_krylov_ilu
	9.49.3	Variable Documentation
		9.49.3.1 THDs_AMG_GS
		9.49.3.2 THDs_CPR_gGS
		9.49.3.3 THDs_CPR_IGS
9.50	itsolver	_csr.c File Reference
		Detailed Description
	9.50.2	Function Documentation

XX CONTENTS

9.50.2.1 fasp_solver_dcsr_itsolver	
9.50.2.2 fasp_solver_dcsr_krylov	
9.50.2.3 fasp_solver_dcsr_krylov_amg	
9.50.2.4 fasp_solver_dcsr_krylov_diag	
9.50.2.5 fasp_solver_dcsr_krylov_ilu	
9.50.2.6 fasp_solver_dcsr_krylov_ilu_M	
9.50.2.7 fasp_solver_dcsr_krylov_schwarz	
9.51 itsolver_mf.c File Reference	
9.51.1 Detailed Description	
9.51.2 Function Documentation	
9.51.2.1 fasp_solver_itsolver	
9.51.2.2 fasp_solver_itsolver_init	
9.51.2.3 fasp_solver_krylov	
9.52 itsolver_str.c File Reference	
9.52.1 Detailed Description	
9.52.2 Function Documentation	
9.52.2.1 fasp_solver_dstr_itsolver	
9.52.2.2 fasp_solver_dstr_krylov	
9.52.2.3 fasp_solver_dstr_krylov_blockgs	
9.52.2.4 fasp_solver_dstr_krylov_diag	
9.52.2.5 fasp_solver_dstr_krylov_ilu	
9.53 itsolver_util.inl File Reference	
9.53.1 Detailed Description	
9.54 linklist.inl File Reference	
9.54.1 Detailed Description	
9.54.2 Macro Definition Documentation	
9.54.2.1 LIST_HEAD	
9.54.2.2 LIST_TAIL	
9.55 lu.c File Reference	
9.55.1 Detailed Description	
9.55.2 Function Documentation	
9.55.2.1 fasp_smat_lu_decomp	
9.55.2.2 fasp_smat_lu_solve	
9.56 memory.c File Reference	
9.56.1 Detailed Description	
9.56.2 Function Documentation	
9.56.2.1 fasp_mem_calloc	

CONTENTS xxi

	9.56.2.2	fasp_mem_check
	9.56.2.3	fasp_mem_dcsr_check
	9.56.2.4	fasp_mem_free
	9.56.2.5	fasp_mem_iludata_check
	9.56.2.6	fasp_mem_realloc
	9.56.2.7	fasp_mem_usage
9.56.3	Variable I	Documentation
	9.56.3.1	total_alloc_count
	9.56.3.2	total_alloc_mem
9.57 messa	ge.c File R	teference
9.57.1	Detailed	Description
9.57.2	Function	Documentation
	9.57.2.1	fasp_chkerr
	9.57.2.2	print_amgcomplexity
	9.57.2.3	print_amgcomplexity_bsr
	9.57.2.4	print_cputime
	9.57.2.5	print_itinfo
	9.57.2.6	print_message
9.58 messa	ges.h File	Reference
9.58.1	Detailed	Description
9.58.2	Macro De	efinition Documentation
	9.58.2.1	AMLI_CYCLE
	9.58.2.2	ASCEND
	9.58.2.3	CF_ORDER
	9.58.2.4	CGPT
	9.58.2.5	CLASSIC_AMG
	9.58.2.6	COARSE_AC
	9.58.2.7	COARSE_CR
	9.58.2.8	COARSE_RS
	9.58.2.9	CPFIRST
	9.58.2.10	DESCEND
	9.58.2.11	ERROR_ALLOC_MEM
	9.58.2.12	PERROR_AMG_COARSE_TYPE
	9.58.2.13	BERROR_AMG_COARSEING
	9.58.2.14	ERROR_AMG_INTERP_TYPE
	9.58.2.15	ERROR_AMG_SMOOTH_TYPE
	9.58.2.16	S ERROR_DATA_STRUCTURE238

xxii CONTENTS

9.58.2.18 ERROR_DUMMY_VAR
9.58.2.19 ERROR_INPUT_PAR
9.58.2.20 ERROR_MISC
9.58.2.21 ERROR_NUM_BLOCKS
9.58.2.22 ERROR_OPEN_FILE
9.58.2.23 ERROR_QUAD_DIM
9.58.2.24 ERROR_QUAD_TYPE
9.58.2.25 ERROR_REGRESS
9.58.2.26 ERROR_SOLVER_EXIT
9.58.2.27 ERROR_SOLVER_ILUSETUP
9.58.2.28 ERROR_SOLVER_MAXIT
9.58.2.29 ERROR_SOLVER_MISC
9.58.2.30 ERROR_SOLVER_PRECTYPE
9.58.2.31 ERROR_SOLVER_SOLSTAG
9.58.2.32 ERROR_SOLVER_STAG
9.58.2.33 ERROR_SOLVER_TOLSMALL
9.58.2.34 ERROR_SOLVER_TYPE
9.58.2.35 ERROR_WRONG_FILE
9.58.2.36 FALSE
9.58.2.37 FGPT
9.58.2.38 FPFIRST
9.58.2.39 ILUk
9.58.2.40 ILUt
9.58.2.41 ILUtp
9.58.2.42 INTERP_DIR
9.58.2.43 INTERP_ENG
9.58.2.44 INTERP_STD
9.58.2.45 ISPT
9.58.2.46 MAT_bBSR
9.58.2.47 MAT_bCSR
9.58.2.48 MAT_BSR
9.58.2.49 MAT_CSR
9.58.2.50 MAT_CSRL
9.58.2.51 MAT_FREE
9.58.2.52 MAT_STR
9.58.2.53 MAT_SymCSR

CONTENTS xxiii

9.58.2.54 NL_AMLI_CYCLE
9.58.2.55 NO_ORDER
9.58.2.56 OFF
9.58.2.57 ON
9.58.2.58 PREC_AMG
9.58.2.59 PREC_DIAG
9.58.2.60 PREC_FMG
9.58.2.61 PREC_ILU
9.58.2.62 PREC_NULL
9.58.2.63 PREC_SCHWARZ
9.58.2.64 PRINT_ALL
9.58.2.65 PRINT_MIN
9.58.2.66 PRINT_MORE
9.58.2.67 PRINT_MOST
9.58.2.68 PRINT_NONE
9.58.2.69 PRINT_SOME
9.58.2.70 RUN_FAIL
9.58.2.71 SA_AMG
9.58.2.72 SMOOTHER_BLKOIL
9.58.2.73 SMOOTHER_CG
9.58.2.74 SMOOTHER_GS
9.58.2.75 SMOOTHER_GSOR
9.58.2.76 SMOOTHER_JACOBI
9.58.2.77 SMOOTHER_L1DIAG
9.58.2.78 SMOOTHER_POLY
9.58.2.79 SMOOTHER_SGS
9.58.2.80 SMOOTHER_SGSOR
9.58.2.81 SMOOTHER_SOR
9.58.2.82 SMOOTHER_SSOR
9.58.2.83 SOLVER_AMG
9.58.2.84 SOLVER_BiCGstab
9.58.2.85 SOLVER_CG
9.58.2.86 SOLVER_FMG
9.58.2.87 SOLVER_GCG
9.58.2.88 SOLVER_GMRES
9.58.2.89 SOLVER_MinRes
9.58.2.90 SOLVER_MUMPS

xxiv CONTENTS

	9.58.2.91 SOLVER_SBiCGstab
	9.58.2.92 SOLVER_SCG
	9.58.2.93 SOLVER_SGCG
	9.58.2.94 SOLVER_SGMRES
	9.58.2.95 SOLVER_SMinRes
	9.58.2.96 SOLVER_SUPERLU
	9.58.2.97 SOLVER_SVFGMRES
	9.58.2.98 SOLVER_SVGMRES
	9.58.2.99 SOLVER_UMFPACK
	9.58.2.100SOLVER_VFGMRES
	9.58.2.101SOLVER_VGMRES
	9.58.2.102STOP_MOD_REL_RES
	9.58.2.103STOP_REL_PRECRES
	9.58.2.104STOP_REL_RES
	9.58.2.105SUCCESS
	9.58.2.106TRUE
	9.58.2.107UA_AMG
	9.58.2.108UNPT
	9.58.2.109USERDEFINED
	9.58.2.110V_CYCLE
	9.58.2.111W_CYCLE
9.59 mg_u	itil.inl File Reference
	1 Detailed Description
	cle.c File Reference
9.60.	1 Detailed Description
9.60.	2 Function Documentation
	9.60.2.1 fasp_solver_mgcycle
	9.60.2.2 fasp_solver_mgcycle_bsr
9.61 mgre	cur.c File Reference
9.61.	1 Detailed Description
9.61.	2 Function Documentation
	9.61.2.1 fasp_solver_mgrecur
9.62 order	ing.c File Reference
	1 Detailed Description
9.62.	2 Function Documentation
	9.62.2.1 fasp_aux_dQuickSort
	9.62.2.2 fasp_aux_dQuickSortIndex

CONTENTS XXV

		9.62.2.3	fasp aux iQuickSort	4
			fasp_aux_iQuickSortIndex	
			fasp_aux_merge	
		9.62.2.6	fasp aux msort	
			fasp_aux_unique	
			fasp_BinarySearch	
9.63	parame		Reference	
	•		Description	
			Documentation	
			fasp_param_amg_init	
			fasp_param_amg_print	
		9.63.2.3	fasp_param_amg_set	0
		9.63.2.4	fasp_param_amg_to_prec	0
		9.63.2.5	fasp_param_amg_to_prec_bsr	1
		9.63.2.6	fasp_param_ilu_init	1
		9.63.2.7	fasp_param_ilu_print	1
		9.63.2.8	fasp_param_ilu_set	2
		9.63.2.9	fasp_param_init	2
		9.63.2.10	fasp_param_input_init	3
		9.63.2.11	fasp_param_prec_to_amg	3
		9.63.2.12	fasp_param_prec_to_amg_bsr	3
		9.63.2.13	fasp_param_schwarz_init	4
		9.63.2.14	fasp_param_schwarz_print	4
		9.63.2.15	fasp_param_schwarz_set	4
		9.63.2.16	fasp_param_solver_init	5
		9.63.2.17	fasp_param_solver_print	5
		9.63.2.18	fasp_param_solver_set	5
		9.63.2.19	fasp_precond_data_null	6
9.64	pbcgs.	c File Refe	rence	6
	9.64.1	Detailed	Description	7
	9.64.2	Function	Documentation	В
		9.64.2.1	fasp_solver_bdcsr_pbcgs	В
		9.64.2.2	fasp_solver_dbsr_pbcgs	В
		9.64.2.3	fasp_solver_dcsr_pbcgs	9
		9.64.2.4	fasp_solver_dstr_pbcgs	0
9.65	pbcgs_	mf.c File F	Reference	0
	9.65.1	Detailed	Description	1

xxvi CONTENTS

	9.65.2	Function Documentation
		9.65.2.1 fasp_solver_pbcgs
9.66	pcg.c F	File Reference
	9.66.1	Detailed Description
	9.66.2	Function Documentation
		9.66.2.1 fasp_solver_bdcsr_pcg
		9.66.2.2 fasp_solver_dcsr_pcg
		9.66.2.3 fasp_solver_dstr_pcg
9.67	pcg_m	f.c File Reference
	9.67.1	Detailed Description
	9.67.2	Function Documentation
		9.67.2.1 fasp_solver_pcg
9.68	pgcg.c	File Reference
	9.68.1	Detailed Description
	9.68.2	Function Documentation
		9.68.2.1 fasp_solver_dcsr_pgcg
9.69	pgcg_n	nf.c File Reference
	9.69.1	Detailed Description
	9.69.2	Function Documentation
		9.69.2.1 fasp_solver_pgcg
9.70	pgmres	s.c File Reference
	9.70.1	Detailed Description
	9.70.2	Function Documentation
		9.70.2.1 fasp_solver_bdcsr_pgmres
		9.70.2.2 fasp_solver_dbsr_pgmres
		9.70.2.3 fasp_solver_dcsr_pgmres
		9.70.2.4 fasp_solver_dstr_pgmres
9.71	pgmres	s_mf.c File Reference
	9.71.1	Detailed Description
	9.71.2	Function Documentation
		9.71.2.1 fasp_solver_pgmres
9.72	pminre	s.c File Reference
	9.72.1	Detailed Description
	9.72.2	Function Documentation
		9.72.2.1 fasp_solver_bdcsr_pminres
		9.72.2.2 fasp_solver_dcsr_pminres
		9.72.2.3 fasp_solver_dstr_pminres

CONTENTS xxvii

9.73 pminres_	_mf.c File Reference	. 289
9.73.1	Detailed Description	. 289
9.73.2 F	Function Documentation	. 290
9	9.73.2.1 fasp_solver_pminres	. 290
9.74 precond_	_bsr.c File Reference	. 291
9.74.1	Detailed Description	. 292
9.74.2 F	Function Documentation	. 292
9	9.74.2.1 fasp_precond_dbsr_amg	. 292
9	9.74.2.2 fasp_precond_dbsr_diag	. 292
9	9.74.2.3 fasp_precond_dbsr_diag_nc2	. 293
9	9.74.2.4 fasp_precond_dbsr_diag_nc3	. 294
9	9.74.2.5 fasp_precond_dbsr_diag_nc5	. 295
9	9.74.2.6 fasp_precond_dbsr_diag_nc7	. 296
9	9.74.2.7 fasp_precond_dbsr_ilu	. 297
9	9.74.2.8 fasp_precond_dbsr_nl_amli	. 298
9.75 precond_	_csr.c File Reference	. 298
9.75.1	Detailed Description	. 299
9.75.2 F	Function Documentation	. 299
9	9.75.2.1 fasp_precond_amg	. 299
9	9.75.2.2 fasp_precond_amli	. 300
9	9.75.2.3 fasp_precond_diag	. 300
9	9.75.2.4 fasp_precond_famg	. 300
9	9.75.2.5 fasp_precond_free	. 301
9	9.75.2.6 fasp_precond_ilu	. 301
9	9.75.2.7 fasp_precond_ilu_backward	. 301
9	9.75.2.8 fasp_precond_ilu_forward	. 302
9	9.75.2.9 fasp_precond_nl_amli	. 302
9	9.75.2.10 fasp_precond_schwarz	. 303
9	9.75.2.11 fasp_precond_setup	. 304
9.76 precond_	_str.c File Reference	. 304
9.76.1	Detailed Description	. 305
9.76.2 F	Function Documentation	. 305
9	9.76.2.1 fasp_precond_dstr_blockgs	. 305
9	9.76.2.2 fasp_precond_dstr_diag	. 305
Ş	9.76.2.3 fasp_precond_dstr_ilu0	. 306
9	9.76.2.4 fasp_precond_dstr_ilu0_backward	. 306
9	9.76.2.5 fasp_precond_dstr_ilu0_forward	. 307

xxviii CONTENTS

		9.76.2.6 fasp_precond_dstr_ilu1
		9.76.2.7 fasp_precond_dstr_ilu1_backward
		9.76.2.8 fasp_precond_dstr_ilu1_forward
9.77	pvfgmr	es.c File Reference
	9.77.1	Detailed Description
	9.77.2	Function Documentation
		9.77.2.1 fasp_solver_dbsr_pvfgmres
		9.77.2.2 fasp_solver_dcsr_pvfgmres
9.78	pvfgmr	es_mf.c File Reference
	9.78.1	Detailed Description
	9.78.2	Function Documentation
		9.78.2.1 fasp_solver_pvfgmres
9.79	pvgmre	es.c File Reference
	9.79.1	Detailed Description
	9.79.2	Function Documentation
		9.79.2.1 fasp_solver_bdcsr_pvgmres
		9.79.2.2 fasp_solver_dbsr_pvgmres
		9.79.2.3 fasp_solver_dcsr_pvgmres
		9.79.2.4 fasp_solver_dstr_pvgmres
9.80	pvgmre	es_mf.c File Reference
	9.80.1	Detailed Description
	9.80.2	Function Documentation
		9.80.2.1 fasp_solver_pvgmres
9.81	quadra	ture.c File Reference
	9.81.1	Detailed Description
	9.81.2	Function Documentation
		9.81.2.1 fasp_gauss2d
		9.81.2.2 fasp_quad2d
9.82	rap.c F	ile Reference
	9.82.1	Detailed Description
	9.82.2	Function Documentation
		9.82.2.1 fasp_blas_dcsr_rap2
9.83	schwar	z.f File Reference
	9.83.1	Detailed Description
9.84	schwar	z_setup.c File Reference
		Detailed Description
	9.84.2	Function Documentation

CONTENTS xxix

	9.84.2.1 fasp_schwarz_setup
9.85 smat	.c File Reference
9.85	1 Detailed Description
9.85	2 Function Documentation
	9.85.2.1 fasp_blas_smat_inv
	9.85.2.2 fasp_blas_smat_inv_nc2
	9.85.2.3 fasp_blas_smat_inv_nc3
	9.85.2.4 fasp_blas_smat_inv_nc4
	9.85.2.5 fasp_blas_smat_inv_nc5
	9.85.2.6 fasp_blas_smat_inv_nc7
	9.85.2.7 fasp_iden_free
	9.85.2.8 fasp_smat_identity
	9.85.2.9 fasp_smat_identity_nc2
	9.85.2.10 fasp_smat_identity_nc3
	9.85.2.11 fasp_smat_identity_nc5
	9.85.2.12 fasp_smat_identity_nc7
9.86 smoo	other_bsr.c File Reference
9.86	1 Detailed Description
9.86	2 Function Documentation
	9.86.2.1 fasp_smoother_dbsr_gs
	9.86.2.2 fasp_smoother_dbsr_gs1
	9.86.2.3 fasp_smoother_dbsr_gs_ascend
	9.86.2.4 fasp_smoother_dbsr_gs_descend
	9.86.2.5 fasp_smoother_dbsr_gs_order1
	9.86.2.6 fasp_smoother_dbsr_gs_order2
	9.86.2.7 fasp_smoother_dbsr_ilu
	9.86.2.8 fasp_smoother_dbsr_jacobi
	9.86.2.9 fasp_smoother_dbsr_jacobi1
	9.86.2.10 fasp_smoother_dbsr_jacobi_setup
	9.86.2.11 fasp_smoother_dbsr_sor
	9.86.2.12 fasp_smoother_dbsr_sor1
	9.86.2.13 fasp_smoother_dbsr_sor_ascend
	9.86.2.14 fasp_smoother_dbsr_sor_descend
	9.86.2.15 fasp_smoother_dbsr_sor_order
9.87 smoo	other_csr.c File Reference
9.87	1 Detailed Description
9.87	2 Function Documentation

CONTENTS

	9.87.2.1 fasp_smoother_dcsr_gs
	9.87.2.2 fasp_smoother_dcsr_gs_cf
	9.87.2.3 fasp_smoother_dcsr_ilu
	9.87.2.4 fasp_smoother_dcsr_jacobi
	9.87.2.5 fasp_smoother_dcsr_kaczmarz
	9.87.2.6 fasp_smoother_dcsr_L1diag
	9.87.2.7 fasp_smoother_dcsr_sgs
	9.87.2.8 fasp_smoother_dcsr_sor
	9.87.2.9 fasp_smoother_dcsr_sor_cf
9.88 smoo	ther_csr_cr.c File Reference
9.88.	Detailed Description
9.88.2	2 Function Documentation
	9.88.2.1 fasp_smoother_dcsr_gscr
9.89 smoo	ther_csr_poly.c File Reference
9.89.	Detailed Description
9.89.2	Function Documentation
	9.89.2.1 fasp_smoother_dcsr_poly
	9.89.2.2 fasp_smoother_dcsr_poly_old
9.90 smoo	ther_str.c File Reference
9.90.	Detailed Description
9.90.2	Function Documentation
	9.90.2.1 fasp_generate_diaginv_block
	9.90.2.2 fasp_smoother_dstr_gs
	9.90.2.3 fasp_smoother_dstr_gs1
	9.90.2.4 fasp_smoother_dstr_gs_ascend
	9.90.2.5 fasp_smoother_dstr_gs_cf
	9.90.2.6 fasp_smoother_dstr_gs_descend
	9.90.2.7 fasp_smoother_dstr_gs_order
	9.90.2.8 fasp_smoother_dstr_jacobi
	9.90.2.9 fasp_smoother_dstr_jacobi1
	9.90.2.10 fasp_smoother_dstr_schwarz
	9.90.2.11 fasp_smoother_dstr_sor
	9.90.2.12 fasp_smoother_dstr_sor1
	9.90.2.13 fasp_smoother_dstr_sor_ascend
	9.90.2.14 fasp_smoother_dstr_sor_cf
	9.90.2.15 fasp_smoother_dstr_sor_descend
	9.90.2.16 fasp_smoother_dstr_sor_order

CONTENTS xxxi

9.91	sparse	_block.c File Reference
	9.91.1	Detailed Description
	9.91.2	Function Documentation
		9.91.2.1 fasp_dbsr_getblk
		9.91.2.2 fasp_dbsr_getblk_dcsr
		9.91.2.3 fasp_dcsr_getblk
9.92	sparse	_bsr.c File Reference
	9.92.1	Detailed Description
	9.92.2	Function Documentation
		9.92.2.1 fasp_dbsr_alloc
		9.92.2.2 fasp_dbsr_cp
		9.92.2.3 fasp_dbsr_create
		9.92.2.4 fasp_dbsr_diaginv
		9.92.2.5 fasp_dbsr_diaginv2
		9.92.2.6 fasp_dbsr_diaginv3
		9.92.2.7 fasp_dbsr_diaginv4
		9.92.2.8 fasp_dbsr_diagpref
		9.92.2.9 fasp_dbsr_free
		9.92.2.10 fasp_dbsr_getdiag
		9.92.2.11 fasp_dbsr_getdiaginv
		9.92.2.12 fasp_dbsr_null
		9.92.2.13 fasp_dbsr_trans
9.93	sparse	_coo.c File Reference
	9.93.1	Detailed Description
	9.93.2	Function Documentation
		9.93.2.1 fasp_dcoo_alloc
		9.93.2.2 fasp_dcoo_create
		9.93.2.3 fasp_dcoo_free
		9.93.2.4 fasp_dcoo_shift
9.94	sparse	csr.c File Reference
	9.94.1	Detailed Description
	9.94.2	Function Documentation
		9.94.2.1 fasp_dcsr_alloc
		9.94.2.2 fasp_dcsr_compress
		9.94.2.3 fasp_dcsr_compress_inplace
		9.94.2.4 fasp_dcsr_cp
		9.94.2.5 fasp_dcsr_create

xxxii CONTENTS

		9.94.2.6	fasp_dcsr_	diagpre	f	 	 	 	 	 	 . 370
		9.94.2.7	fasp_dcsr_	free		 	 	 	 	 	 . 370
		9.94.2.8	fasp_dcsr_	getcol .		 	 	 	 	 	 . 371
		9.94.2.9	fasp_dcsr_	getdiag		 	 	 	 	 	 . 371
		9.94.2.10	fasp_dcsr_	multicol	oring	 	 	 	 	 	 . 372
		9.94.2.11	fasp_dcsr_	null		 	 	 	 	 	 . 373
		9.94.2.12	fasp_dcsr_	perm .		 	 	 	 	 	 . 373
		9.94.2.13	fasp_dcsr_	regdiag		 	 	 	 	 	 . 374
			fasp_dcsr_								
		9.94.2.15	fasp_dcsr_	sort		 	 	 	 	 	 . 375
		9.94.2.16	fasp_dcsr_	symdiag	yscale	 	 	 	 	 	 . 376
		9.94.2.17	fasp_dcsr_	sympat		 	 	 	 	 	 . 376
		9.94.2.18	fasp_dcsr_	trans .		 	 	 	 	 	 . 377
		9.94.2.19	fasp_icsr_c	р		 	 	 	 	 	 . 378
		9.94.2.20	fasp_icsr_c	create .		 	 	 	 	 	 . 378
		9.94.2.21	fasp_icsr_t	ree		 	 	 	 	 	 . 379
		9.94.2.22	fasp_icsr_i	null		 	 	 	 	 	 . 379
		9.94.2.23	fasp_icsr_t	rans		 	 	 	 	 	 . 379
9.95	sparse_	_csrl.c File	Reference			 	 	 	 	 	 . 380
9	9.95.1	Detailed D	escription			 	 	 	 	 	 . 380
9	9.95.2	Function D	Oocumenta	tion		 	 	 	 	 	 . 380
			fasp_dcsrl								
			fasp_dcsrl								
	•	_str.c File F									
		Detailed D	•								
9	9.96.2	Function D	Oocumenta	tion		 	 	 	 	 	 . 382
		9.96.2.1	fasp_dstr_	alloc		 	 	 	 	 	 . 382
			fasp_dstr_								
			fasp_dstr_								
			fasp_dstr_								
			fasp_dstr_								
		_util.c File F									
		Detailed D									
9	9.97.2	Function D									
			fasp_spars								
			fasp_spars								
		9.97.2.3	fasp_spars	e_abybı	ms	 	 	 	 	 	 . 386

CONTENTS xxxiii

0.07.0.4.7		
1-1 -		
, _ ,		
9.98 spbcgs.c File Reference		
	bbcgs	
•	ocgs	
•	ocgs	
•	ocgs	
9.99 spcg.c File Reference		
·		
	ocg	
	og	
•	g	
9.100spgmres.c File Reference		
	ogmres	
	gmres	
	gmres	
	ımres	
9.101spminres.c File Reference		
	ominres	
	minres	
	ninres	
9.102spvgmres.c File Reference		
1 0 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1		

XXXIV CONTENTS

9.102.1 Detailed Description
9.102.2 Function Documentation
9.102.2.1 fasp_solver_bdcsr_spvgmres
9.102.2.2 fasp_solver_dbsr_spvgmres
9.102.2.3 fasp_solver_dcsr_spvgmres
9.102.2.4 fasp_solver_dstr_spvgmres
9.103threads.c File Reference
9.103.1 Detailed Description
9.103.2 Function Documentation
9.103.2.1 FASP_GET_START_END
9.104timing.c File Reference
9.104.1 Detailed Description
9.104.2 Function Documentation
9.104.2.1 fasp_gettime
9.105vec.c File Reference
9.105.1 Detailed Description
9.105.2 Function Documentation
9.105.2.1 fasp_dvec_alloc
9.105.2.2 fasp_dvec_cp
9.105.2.3 fasp_dvec_create
9.105.2.4 fasp_dvec_free
9.105.2.5 fasp_dvec_isnan
9.105.2.6 fasp_dvec_maxdiff
9.105.2.7 fasp_dvec_null
9.105.2.8 fasp_dvec_rand
9.105.2.9 fasp_dvec_set
9.105.2.10fasp_dvec_symdiagscale
9.105.2.11fasp_ivec_alloc
9.105.2.12fasp_ivec_create
9.105.2.13fasp_ivec_free
9.105.2.14fasp_ivec_set
9.106wrapper.c File Reference
9.106.1 Detailed Description
9.106.2 Function Documentation
9.106.2.1 fasp_fwrapper_amg
9.106.2.2 fasp_fwrapper_krylov_amg
9.106.2.3 fasp_wrapper_dbsr_krylov_amg

CONTENTS		XXXV
	9.106.2.4 fasp_wrapper_dcoo_dbsr_krylov_amg	
Index		423

## Introduction

Over the last few decades, researchers have expended significant effort on developing efficient iterative methods for solving discretized partial differential equations (PDEs). Though these efforts have yielded many mathematically optimal solvers such as the multigrid method, the unfortunate reality is that multigrid methods have not been much used in practical applications. This marked gap between theory and practice is mainly due to the fragility of traditional multigrid (MG) methodology and the complexity of its implementation. We aim to develop techniques and the corresponding software that will narrow this gap, specifically by developing mathematically optimal solvers that are robust and easy to use in practice.

We believe that there is no one-size-for-all solution method for discrete linear systemsfrom different applications. And, efficient iterative solvers can be constructed by taking the properties of PDEs and discretizations into account. In this project, we plan to construct a pool of discrete problems arising from partial differential equations (PDEs) or PDE systems and efficient linear solvers for these problems. We mainly utilize the methodology of Auxiliary Space Preconditioning (ASP) to construct efficient linear solvers. Due to this reason, this software package is called Fast Auxiliary Space Preconditioning or FASP for short.

FASP contains the kernel part and several applications (ranging from fluid dynamics to reservoir simulation). The kernel part is open-source and licensed under GNU Lesser General Public License or LGPL version 3.0 or later. Some of the applications contain contributions from and owned partially by other parties.

For the moment, FASP is under alpha testing. If you wish to obtain a current version of FASP or you have any questions, feel free to contact us at faspdev@gmail.com.

This software distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

2	Introduction

# How to obtain FASP

For the moment, FASP is still under alpha testing. You need a password to download the package. Sorry about it!

The most updated version of FASP can be downloaded from

```
http://fasp.sourceforge.net/download/faspsolver.zip
```

We use HG (Mecurial) as our main version control tool. HG is easy to use and it is available at all OS platforms. For people who is interested in the developer version, you can obtain the FASP package with hg:

\$ hg clone https://faspusers@bitbucket.org/fasp/faspsolver

will give you the developer version of the FASP package.

How to obtain FASP

# **Building and Installation**

This is a simple instruction on building and testing. For more details, please refer to the README files and the short User's Guide in "faspsolver/doc/".

To compile, you need a Fortran and a C compiler. First, you can type in the "faspsolver/" root directory:

\$ make config

which will config the environment automatically. And, then, you can need to type:

\$ make install

which will make the FASP shared static library and install to PREFIX/. By default, FASP libraries and executables will be installed in the FASP home directory "faspsolver/".

There is a simple GUI tool for building and installing FASP included in the package. You need Tcl/Tk support in your computer. You may call this GUI by run in the root directory:

\$ wish fasp install.tcl

If you need to see the detailed usage of "make" or need any help, please type:

\$ make help

After installation, tutorial examples can be found in "tutorial/".

Building a	and In	stalla	atioi
------------	--------	--------	-------

# **Developers**

#### Project Leader:

• Xu, Jinchao (Penn State University, USA)

#### Current Developers (in alphabetic order):

- Feng, Chunsheng (Xiangtan University, China)
- Hu, Xiaozhe (Penn State University, USA)
- Li, Zheng (Xiangtan University, China)
- Shu, Shi (Xiangtan University, China)
- Wang, Ziteng (Peking University, China)
- Yue, Xiaoqiang (Xiangtan University, China)
- Zhang, Chensong (Chinese Academy of Sciences, China)
- Zikatanov, Ludmil (Penn State University, USA)

#### With contributions from (in alphabetic order):

- · Brannick, James (Penn State University, USA)
- · Cao, Fei (Penn State University, USA)
- Huang, Feiteng (Sichuang University, China)
- · Huang, Xuehai (Shanghai Jiaotong University, China)
- Qiao, Changhe (Penn State University, USA)
- Yang, Kai (Penn State University, USA)
- Zhang, Shiquan (Sichuan University, China)
- Zhang, Shuo (Chinese Academy of Sciences, China)
- Zhang, Weifeng (Kunming University of Science and Technology, China)

8 Developers

• Zhou, Zhiyang (Xiangtan University, China)

Project Coordinator:

• Zhang, Chensong (Chinese Academy of Sciences, China)

# Doxygen

We use Doxygen as our automatically documentation generator which will make our future maintainance minimized. You can obtain the software (Windows, Linux and OS X) as well as its manual on the official website

http://www.doxygen.org

For an oridinary user, Doxygen is completely trivial to use. We only need to use some special marker in the usual comment as we put in c-files.



# **Data Structure Index**

## 6.1 Data Structures

Here are the data structures with brief descriptions:

AMG_data	
Data for AMG solvers	19
AMG_data_bsr	
Data for multigrid levels. (BSR format)	20
AMG_param	
Parameters for AMG solver	21
block_BSR	
Block REAL matrix format for reservoir simulation	23
block_dCSRmat	•
Block REAL CSR matrix format	24
block_dvector  Block REAL vector structure	0.5
block iCSRmat	20
Block INT CSR matrix format	25
block ivector	20
Block INT vector structure	26
block Reservoir	
Block REAL matrix format for reservoir simulation	26
dBSRmat	
Block sparse row storage matrix of REAL type	27
dCOOmat	
Sparse matrix of REAL type in COO (or IJ) format	28
dCSRLmat	
Sparse matrix of REAL type in CSRL format	29
dCSRmat	
Sparse matrix of REAL type in CSR format	29
ddenmat	
Dense matrix of REAL type	30
dSTRmat	04
Structure matrix of REAL type	31
Vector with n entries of REAL type	21
grid2d	ا ق
Two dimensional grid data structure	30
Two dimensional grid data structure	02

12 Data Structure Index

iCOOmat		
iCSRmat	-1	34
IOSHIIIai		35
idenmat		
	Dense matrix of INT type	36
ILU_data		
	Data for ILU setup	36
ILU_para	m	
		37
input_pai		
	harden and a second	37
itsolver_p		
	Parameters passed to iterative solvers	44
ivector	And the second s	
	Vector with n entries of INT type	45
Link		
المعالما		46
linked_lis		40
mana a maat		46
mxv_mat		47
procend	Matrix-vector multiplication, replace the actual matrix	47
precond	Preconditioner data and action	47
procend	block_data	47
precond_		48
nrecond	block reservoir data	40
procoria_		49
precond	· · · · · · · · · · · · · · · · · · ·	70
procenta_		52
precond	data_bsr	Ŭ-
p. 000u_		54
precond		•
_	· <del>-</del>	55
precond_		
		57
precond_	•	
		57
precond_	FASP_blkoil_data	
_		58
Schwarz_	· · · · · · · · · · · · · · · · · · ·	
	Data for Schwarz methods	62
Schwarz_	_param	
	Parameters for Schwarz method	63

# File Index

## 7.1 File List

Here is a list of all documented files with brief descriptions:

amg.c		
	AMG method as an iterative solver (main file)	65
amg_set	up_aggregation_bsr.inl	
	Utilies for multigrid cycles in BSR format	66
amg_set	up_aggregation_csr.inl	
	Utilies for multigrid cycles for CSR matrices	66
amg_set	· <del>-</del>	
	Brannick-Falgout compatible relaxation based AMG: SETUP phase	66
amg_set		
	Ruge-Stuben AMG: SETUP phase	67
amg_set	•—	
	Smoothed aggregation AMG: SETUP phase	69
amg_set		70
	Unsmoothed aggregation AMG: SETUP phase	70
amg_solv		74
omliroou	Algebraic multigrid iterations: SOLVE phase	/ 1
amlirecui	Abstract AMLI multilevel iteration – recursive version	74
array.c	Austract Afficial multilever iteration – recursive version	74
array.c	Array operations	77
blas_arra	• •	' '
Diao_arro	BLAS operations for arrays	81
blas bcs		•
	BLAS operations for block_dCSRmat matrices	86
blas bsr.		
_	BLAS operations for dBSRmat matrices	89
blas_csr.	C	
	BLAS operations for dCSRmat matrices	94
blas_csrl		
	BLAS operations for dCSRLmat matrices	01
blas_sma	at.c	
	BLAS operations for small full matrix	02
blas_str.o		
	BLAS operations for dSTRmat matrices	21

14 File Index

blas_vec.c
BLAS operations for vectors
checkmat.c
Check matrix properties
coarsening_cr.c  Coarsening with Brannick-Falgout strategy
coarsening_rs.c
Coarsening with a modified Ruge-Stuben strategy
convert.c  Some utilities for format conversion
doxygen.h
Main page for Doygen documentation
eigen.c Simple subroutines for compute the extreme eigenvalues
factor.f
LU factoraization for CSR matrix
famg.c  Full AMG method as an iterative solver (main file)
fasp.h
Main header file for FASP
fasp_block.h
Main header file for FASP (block matrices)
Abstract non-recursive full multigrid cycle
formats.c
Matrix format conversion routines
Givens transformation
gmg_poisson.c
GMG method as an iterative solver for Poisson Problem
gmg_util.inl  Routines for GMG solvers
graphics.c
Functions for graphical output
ilu.f  ILU routines for preconditioning adapted from SPARSEKIT
ilu_setup_bsr.c
Setup Incomplete LU decomposition for dBSRmat matrices
ilu_setup_csr.c  Setup of ILU decomposition for dCSRmat matrices
ilu setup str.c
Setup of ILU decomposition for dSTRmat matrices
init.c Initialize important data structures
initialize important data structures
Read input parameters
interface_mumps.c
Interface to MUMPS direct solvers
Interface to SAMG
interface_superlu.c
Interface to SuperLU direct solvers
interface_umfpack.c Interface to UMFPACK direct solvers

7.1 File List

interpolation _em.c interpolation operators for AMG based on energy-min interpolation operators in put/output subroutines itsolver_bsr.c iterative solvers for dBSRmat matrices itsolver_bsr.c iterative solvers for dBSRmat matrices itsolver_csr.c iterative solvers for dCSRmat matrices itsolver_mf.c iterative solvers with matrix-free spmv itsolver_str.c iterative solvers with matrix-free spmv itsolver_str.c iterative solvers for dSTRmat matrices itsolver_utili.in in Routines for iterative solvers in dSTRmat matrices itsolver_utili.in in Routines for iterative solvers in discolver_str.c iterative solver_str.c iterative solver_str.c iterative solver_str.c iterative solver_str.c iterative solver_str.c iterative solver_str.c	interpolation.c
Interpolation operators for AMG based on energy-min  io.c  Matrix-vector input/output subroutines  Itsolver_bcsr.c  Iterative solvers for block_dCSRmat matrices  Iterative solvers for dBSRmat matrices  Iterative solvers for dBSRmat matrices  Iterative solvers for dCSRmat matrices  Iterative solvers for dCSRmat matrices  Iterative solvers with matrix-free spmv  Iterative solvers with matrix-free spmv  Iterative solvers with matrix-free spmv  Iterative solvers for dSTRmat matrices  Iterative solvers with matrix-free spmv  Iterative solvers for dSTRmat matrices  Iterative solvers with matrix-free spmv  Iterative solvers for dSTRmat matrices  Iterative solvers with matrix-free spmv  Iterative solvers with matrix-free spmv  Iterative solvers for dSTRmat matrices  Iterative solvers with matrix-free spmv  Iterative solvers with matrix-free spmv  Iterative solvers for dSTRmat matrices  Iterative solvers with matrix-free spmv  Iterative solvers with matrix-free spmv  Iterative solvers with matrices  Iterative solvers with solvers spmv	Interpolation operators for AMG
itsolver_bosr.c Iterative solvers for block_dCSRmat matrices Itsolver_bosr.c Iterative solvers for block_dCSRmat matrices Itsolver_bsr.c Iterative solvers for dBSRmat matrices Iterative solvers for dBSRmat matrices Iterative solvers for dCSRmat matrices Iterative solvers for dCSRmat matrices Iterative solvers with matrix-free spmv Iterative solvers with matrix-free spmv Iterative solvers for dSTRmat matrices Iterative solvers for dSTRmat matri	interpolation_em.c
Matrix-vector input/output subroutines itsolver_bcsr.c lterative solvers for block_dCSRmat matrices .20 itsolver_bsr.c lterative solvers for dBSRmat matrices .20 itsolver_bsr.c lterative solvers for dCSRmat matrices .20 itsolver_csr.c lterative solvers for dCSRmat matrices .21 itsolver_mr.c lterative solvers with matrix-free spmv .21 itsolver_str.c lterative solvers for dSTRmat matrices .22 itisolver_util.inl Routines for iterative solvers .22 linklist.inl Utilies for link list data structure .22 lu.c LU decomposition and direct solve for dense matrix .22 memory.c Memory allocation and deallocation .22 message.c Output some useful messages .23 messages.h Definition of all kinds of messages, including error messages, solver types, etc .23 mg_util.inl Routines for algebraic multigrid cycles .25 mgcycle.c Abstract non-recursive multigrid cycle mgrecur.c Abstract non-recursive multigrid cycle mgrecur.c A collection of ordering, merging, removing duplicated integers functions .25 parameters.c Initialize, set, or print input data and parameters .25 pcgs.c Krylov subspace methods – Preconditioned BiCGstab pbcgs_mrl.c Krylov subspace methods – Preconditioned Gingate gradient .27 pcg.c Krylov subspace methods – Preconditioned Generalized CG .27 pgcg_nfl.c Krylov subspace methods – Preconditioned Generalized CG .27 pgmcs.c Krylov subspace methods – Preconditioned Generalized CG .27 pgmcs.c Krylov subspace methods – Preconditioned Generalized CG .27 pgmcs.c Krylov subspace methods – Preconditioned Generalized CG .27 pgmcs.c Krylov subspace methods – Preconditioned Generalized CG .28 pgmres_mrl.c	Interpolation operators for AMG based on energy-min
itsolver_bcsr.c Iterative solvers for block_dCSRmat matrices Iterative solvers for dBSRmat matrices Iterative solvers for dBSRmat matrices Iterative solvers for dCSRmat matrices Iterative solvers for dCSRmat matrices Iterative solvers for dCSRmat matrices Iterative solvers for dSTRmat matri	io.c
Iterative solvers for block_dCSRmat matrices itsolver_bsr.c Iterative solvers for dBSRmat matrices itsolver_csr.c Iterative solvers for dCSRmat matrices itsolver_mrl.c Iterative solvers for dCSRmat matrices iterative solvers for dCSRmat matrices iterative solvers for dCSRmat matrices iterative solvers for dSTRmat matrices  22 Indicative solvers for dSTRmat matrices 22 Indication for literative solvers 23 Indication for literative solvers 24 Indication for solvers for dense matrix 25 Indication for solvers for dense matrix 26 Indication for solvers for dense matrix 27 Indication for solvers for dense matrix 28 Indication for solvers for dense matrix 29 Indication for solvers for dense matrix 29 Indication for solvers for dense matrix 20 Indication for solvers for dense matrix 20 Indication for solvers for dense matrix 21 Indication for solvers for dense matrix 22 Indication for solvers for dense matrix 22 Indication for solvers for dense for dense matrix 21 Indication for solvers for dense for	Matrix-vector input/output subroutines
itsolver_bsr.c Iterative solvers for dBSRmat matrices itsolver_csr.c Iterative solvers for dCSRmat matrices itsolver_mf.c Iterative solvers with matrix-free spmv itsolver_str.c Iterative solvers with matrix-free spmv itsolver_util.c Iterative solvers for dSTRmat matrices itsolver_util.inl Routines for iterative solvers Iterative solvers for dSTRmat matrices itsolver_util.inl Routines for iterative solvers Iterative solvers Iterative solvers for dSTRmat matrices Iterative solvers fo	itsolver_bcsr.c
Iterative solvers for dBSRmat matrices  Itsolver_csr.c  Iterative solvers for dCSRmat matrices  Iterative solvers for dCSRmat matrices  Iterative solvers with matrix-free spmv  Itsolver_mt.c  Iterative solvers for dSTRmat matrices  Iterative solv	Iterative solvers for block_dCSRmat matrices
itsolver_csr.c  Iterative solvers for dCSRmat matrices  Iterative solvers with matrix-free spmv  Iterative solvers with matrix-free spmv  Iterative solvers for dSTRmat matrices  Iterative solvers for iterative solvers  Inklist.inl  Utilies for link list data structure  LU decomposition and direct solve for dense matrix  22  LU decomposition and deallocation  Memory allocation and deallocation  22  message.c  Output some useful messages  Messages.h  Definition of all kinds of messages, including error messages, solver types, etc  33  messages.h  Routines for algebraic multigrid cycles  34  mg_util.inl  Routines for algebraic multigrid cycles  35  mgcycle.c  Abstract non-recursive multigrid cycle  36  mgrecur.c  Abstract multigrid cycle – recursive version  37  A collection of ordering, merging, removing duplicated integers functions  38  29  parameters.c  Initialize, set, or print input data and parameters  pbcgs.c  Krylov subspace methods – Preconditioned BiCGstab  pbcgs_mr.c  Krylov subspace methods – Preconditioned BiCGstab (matrix free)  27  pcg_mf.c  Krylov subspace methods – Preconditioned conjugate gradient (matrix free)  27  pcg_mf.c  Krylov subspace methods – Preconditioned Generalized CG  Krylov subspace methods – Preconditioned Generalized CG  Krylov subspace methods – Preconditioned Generalized CG  Krylov subspace methods – Preconditioned Generalized CG (matrix free)  27  pgg_mres_mt.c  Krylov subspace methods – Preconditioned Generalized CG (matrix free)  27  pgg_mres_mt.c	itsolver_bsr.c
Iterative solvers for dCSRmat matrices  itsolver_mf.c  Iterative solvers with matrix-free spmv  itsolver_str.c  Iterative solvers for dSTRmat matrices  22 linklist.inl  Utilies for link list data structure  22 lu.c  LU decomposition and direct solve for dense matrix  22 memory.c  Memory allocation and deallocation  22 message.c  Output some useful messages  23 messages.h  Definition of all kinds of messages, including error messages, solver types, etc  23 mg_util.inl  Routines for algebraic multigrid cycles  25 mgcycle.c  Abstract non-recursive multigrid cycle  26 mgrecur.c  Abstract multigrid cycle – recursive version  27 ordering.c  A collection of ordering, merging, removing duplicated integers functions  28 parameters.c  Initialize, set, or print input data and parameters  26 plogs.c  Krylov subspace methods – Preconditioned BiCGstab  plogs_mf.c  Krylov subspace methods – Preconditioned BiCGstab (matrix free)  27 pcg.c  Krylov subspace methods – Preconditioned conjugate gradient (matrix free)  27 pcg.g  Krylov subspace methods – Preconditioned Generalized CG  Krylov subspace methods – Preconditioned Generalized CG (matrix free)  28 pgmres_mf.c  Krylov subspace methods – Preconditioned Generalized CG (matrix free)  28 pgmres_mf.c	Iterative solvers for dBSRmat matrices
itsolver_mf.c Iterative solvers with matrix-free spmv Iterative solvers for dSTRmat matrices Iterative solvers Routines for iterative solvers Routines for iterative solvers  Iu.c  LU decomposition and direct solve for dense matrix  LU decomposition and direct solve for dense matrix  memory.c  Memory allocation and deallocation  message.c  Output some useful messages  messages.h  Definition of all kinds of messages, including error messages, solver types, etc  mg_util.inl  Routines for algebraic multigrid cycles  mgcycle.c  Abstract non-recursive multigrid cycle  Abstract non-recursive multigrid cycle  A collection of ordering, merging, removing duplicated integers functions  25 parameters.c  Initialize, set, or print input data and parameters  pbcgs.c  Krylov subspace methods – Preconditioned BiCGstab (matrix free)  pcg_mf.c  Krylov subspace methods – Preconditioned BiCGstab (matrix free)  pcg_mf.c  Krylov subspace methods – Preconditioned Generalized CG  Krylov subspace methods – Preconditioned Generalized CG (matrix free)  27 pgg_mf.c  Krylov subspace methods – Preconditioned Generalized CG (matrix free)  28 pgmres_mf.c	itsolver_csr.c
Iterative solvers with matrix-free spmv itsolver_str.c therative solvers for dSTRmat matrices	Iterative solvers for dCSRmat matrices
itsolver_str.c	itsolver mf.c
itsolver_str.c	Iterative solvers with matrix-free spmv
Iterative solvers for dSTRmat matrices  itsolver_util.inl  Routines for iterative solvers  22 linklist.inl  Utilies for link list data structure  23 LU.C  LU decomposition and direct solve for dense matrix  24 memory.c  Memory allocation and deallocation  25 Memory allocation and deallocation  26 Memory allocation and deallocation  27 message.c  Output some useful messages  28 messages.h  Definition of all kinds of messages, including error messages, solver types, etc  29 mg_util.inl  Routines for algebraic multigrid cycles  25 mgcycle.c  Abstract non-recursive multigrid cycle  Abstract multigrid cycle – recursive version  26 ordering.c  A collection of ordering, merging, removing duplicated integers functions  27 parameters.c  Initialize, set, or print input data and parameters  28 pbcgs.mf.c  Krylov subspace methods – Preconditioned BiCGstab (matrix free)  29 pcg.c  Krylov subspace methods – Preconditioned conjugate gradient  27 pcg_mf.c  Krylov subspace methods – Preconditioned Generalized CG  Krylov subspace methods – Preconditioned Generalized CG (matrix free)  27 pgg_mres_mf.c  Krylov subspace methods – Preconditioned Generalized CG (matrix free)  28 pgmres_mf.c	·
itsolver_util.inl Routines for iterative solvers Routines for iterative solvers Routines for iterative solvers Routines for link list data structure LU decomposition and direct solve for dense matrix LU decomposition and direct solve for dense matrix Remmory.c Memory allocation and deallocation Routinessages. Output some useful messages Ressages.h Definition of all kinds of messages, including error messages, solver types, etc Routines for algebraic multigrid cycles Routines for algebraic multigrid cycles Routines for algebraic multigrid cycle Abstract non-recursive multigrid cycle Rorecurc Abstract multigrid cycle – recursive version A collection of ordering, merging, removing duplicated integers functions A collection of ordering, merging, removing duplicated integers functions Roylov subspace methods – Preconditioned BiCGstab Roylov subspace methods – Preconditioned BiCGstab (matrix free) Roylov subspace methods – Preconditioned BiCGstab (matrix free) Roylov subspace methods – Preconditioned conjugate gradient Roylov subspace methods – Preconditioned Conjugate gradient (matrix free) Roylov subspace methods – Preconditioned Generalized CG (matrix free) Roylov subspace methods – Preconditioned Generalized CG (matrix free) Roylov subspace methods – Preconditioned Generalized CG (matrix free) Roylov subspace methods – Preconditioned Generalized CG (matrix free) Roylov subspace methods – Preconditioned Generalized CG (matrix free) Roylov subspace methods – Preconditioned Generalized CG (matrix free) Roylov subspace methods – Preconditioned Generalized CG (matrix free)	
Routines for iterative solvers	
linklist.inI Utilies for link list data structure	
Utilies for link list data structure	
lu.c  LU decomposition and direct solve for dense matrix	
LU decomposition and direct solve for dense matrix  memory.c  Memory allocation and deallocation  Memory allocation and deallocation  22 message.c  Output some useful messages  Definition of all kinds of messages, including error messages, solver types, etc  Memory algobraic multigrid cycles  mg_util.inl  Routines for algebraic multigrid cycles  mgrecur.c  Abstract non-recursive multigrid cycle  mgrecur.c  Abstract multigrid cycle – recursive version  25 ordering.c  A collection of ordering, merging, removing duplicated integers functions  25 parameters.c  Initialize, set, or print input data and parameters  Exployes.c  Krylov subspace methods – Preconditioned BiCGstab  bcgs_mf.c  Krylov subspace methods – Preconditioned BiCGstab (matrix free)  27 pcg.c  Krylov subspace methods – Preconditioned conjugate gradient  27 pcg_mf.c  Krylov subspace methods – Preconditioned Conjugate gradient (matrix free)  27 pcg_mf.c  Krylov subspace methods – Preconditioned Generalized CG  Krylov subspace methods – Preconditioned Generalized CG  Krylov subspace methods – Preconditioned Generalized CG  Krylov subspace methods – Preconditioned Generalized CG (matrix free)  27 pgcg_mf.c  Krylov subspace methods – Preconditioned Generalized CG (matrix free)  27 pgcg_mf.c  Krylov subspace methods – Preconditioned Generalized CG (matrix free)  28 pgmres_mf.c	
memory.c Memory allocation and deallocation	
Memory allocation and deallocation	
message.c Output some useful messages Definition of all kinds of messages, including error messages, solver types, etc 23 mg_util.inl Routines for algebraic multigrid cycles grecur.c Abstract non-recursive multigrid cycle Abstract multigrid cycle – recursive version Abstract multigrid cycle – recursive version Ac collection of ordering, merging, removing duplicated integers functions parameters.c Initialize, set, or print input data and parameters Initialize, set, or print input data and parameters Exploses.c Krylov subspace methods – Preconditioned BiCGstab BiCGs	
Output some useful messages  messages.h  Definition of all kinds of messages, including error messages, solver types, etc  ang_util.inl  Routines for algebraic multigrid cycles  Abstract non-recursive multigrid cycle  Abstract multigrid cycle - recursive version  ordering.c  A collection of ordering, merging, removing duplicated integers functions  a collection of ordering, merging, removing duplicated integers functions  parameters.c  Initialize, set, or print input data and parameters  bcgs.c  Krylov subspace methods - Preconditioned BiCGstab  ckrylov subspace methods - Preconditioned BiCGstab (matrix free)  ccc  Krylov subspace methods - Preconditioned conjugate gradient  crypcg.c  Krylov subspace methods - Preconditioned conjugate gradient (matrix free)  ccc  Krylov subspace methods - Preconditioned Generalized CG  ccc  Krylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  Krylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  Krylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  Krylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  Krylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  Krylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  Krylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  Krylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  Krylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  Krylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  ccc  Krylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  ccc  Rrylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  ccc  Rrylov subspace methods - Preconditioned Generalized CG (matrix free)  ccc  ccc  Rrylov subspace methods - Preconditioned Generalized CG (matrix free)	·
messages.h Definition of all kinds of messages, including error messages, solver types, etc 23 mg_util.inl Routines for algebraic multigrid cycles	
Definition of all kinds of messages, including error messages, solver types, etc  mg_util.inl Routines for algebraic multigrid cycles	
mg_util.inl Routines for algebraic multigrid cycles	
Routines for algebraic multigrid cycles	
mgcycle.c Abstract non-recursive multigrid cycle	
Abstract non-recursive multigrid cycle	
mgrecur.c Abstract multigrid cycle – recursive version	
Abstract multigrid cycle – recursive version	
ordering.c A collection of ordering, merging, removing duplicated integers functions	
A collection of ordering, merging, removing duplicated integers functions	5 ,
parameters.c     Initialize, set, or print input data and parameters	
Initialize, set, or print input data and parameters	
pbcgs.c    Krylov subspace methods – Preconditioned BiCGstab	·
Krylov subspace methods – Preconditioned BiCGstab	
pbcgs_mf.c    Krylov subspace methods – Preconditioned BiCGstab (matrix free)	
Krylov subspace methods – Preconditioned BiCGstab (matrix free)	
pcg.c  Krylov subspace methods – Preconditioned conjugate gradient	• • -
Krylov subspace methods – Preconditioned conjugate gradient	Krylov subspace methods – Preconditioned BiCGstab (matrix free)
pcg_mf.c  Krylov subspace methods – Preconditioned conjugate gradient (matrix free)	· · ·
Krylov subspace methods – Preconditioned conjugate gradient (matrix free)	Krylov subspace methods – Preconditioned conjugate gradient
pgcg.c  Krylov subspace methods – Preconditioned Generalized CG	• •
Krylov subspace methods – Preconditioned Generalized CG	Krylov subspace methods – Preconditioned conjugate gradient (matrix free)
pgcg_mf.c  Krylov subspace methods – Preconditioned Generalized CG (matrix free)	
Krylov subspace methods – Preconditioned Generalized CG (matrix free)	Krylov subspace methods – Preconditioned Generalized CG
pgmres.c  Krylov subspace methods – Preconditioned GMRes	
Krylov subspace methods – Preconditioned GMRes	Krylov subspace methods – Preconditioned Generalized CG (matrix free)
pgmres_mf.c	
	Krylov subspace methods – Preconditioned GMRes
Krylov subspace methods – Preconditioned GMRes (matrix free)	
	Krylov subspace methods – Preconditioned GMRes (matrix free)

16 File Index

pminres.c
Krylov subspace methods – Preconditioned minimal residual
pminres_mf.c  Krylov subspace methods – Preconditioned minimal residual (matrix free)
precond_bsr.c
Preconditioners for dBSRmat matrices
precond_csr.c  Preconditioners for dCSPmet metrices
Preconditioners for dCSRmat matrices
Preconditioners for dSTRmat matrices
pvfgmres.c
Krylov subspace methods – Preconditioned variable-restarting flexible GMRes
Krylov subspace methods – Preconditioned variable-restarting flexible GMRes (matrix free) 313
pvgmres.c
Krylov subspace methods – Preconditioned variable-restart GMRes
<pre>pvgmres_mf.c</pre>
quadrature.c
Quadrature rules
rap.c R*A*P driver
schwarz.f
Schwarz smoothers
schwarz_setup.c  Setup phase for the Schwarz methods
smat.c
Simple operations for small full matrices in row-major format
smoother_bsr.c
Smoothers for dBSRmat matrices
Smoothers for dCSRmat matrices
smoother_csr_cr.c
Smoothers for dCSRmat matrices using compatible relaxation
smoother_csr_poly.c  Smoothers for dCSRmat matrices using poly. approx. to A^{-1}
smoother_str.c
Smoothers for dSTRmat matrices
sparse_block.c Sparse matrix block operations
sparse_bsr.c
Sparse matrix operations for dBSRmat matrices
sparse_coo.c  Sparse matrix operations for dCOOmat matrices
sparse csr.c
Sparse matrix operations for dCSRmat matrices
sparse_csrl.c
Sparse matrix operations for dCSRLmat matrices
Sparse matrix operations for dSTRmat matrices
sparse_util.c
Routines for sparse matrix operations
spbcgs.c  Krylov subspace methods – Preconditioned BiCGstab with safe net
,

7.1 File List

spcg.c	
	Krylov subspace methods – Preconditioned conjugate gradient with safe net
spgmres.	.c
	Krylov subspace methods – Preconditioned GMRes with safe net
spminres	S.C
	Krylov subspace methods – Preconditioned minimal residual with safe net
spvgmre	S.C
	Krylov subspace methods – Preconditioned variable-restart GMRes with safe net
threads.c	
	Get and set number of threads and assigne work load for each thread
timing.c	
	Timing subroutines
vec.c	
	Simple operations for vectors
wrapper.	С
	Wrappers for accessing functions by advanced users

18	File Index

# **Data Structure Documentation**

## 8.1 AMG\_data Struct Reference

Data for AMG solvers.

```
#include <fasp.h>
```

#### **Data Fields**

SHORT max\_levels

max number of levels

· SHORT num levels

number of levels in use <= max levels

dCSRmat A

pointer to the matrix at level level\_num

dCSRmat R

restriction operator at level level\_num

dCSRmat P

prolongation operator at level level\_num

dvector b

pointer to the right-hand side at level level\_num

dvector x

pointer to the iterative solution at level level\_num

· ivector cfmark

pointer to the CF marker at level level\_num

• INT ILU\_levels

number of levels use ILU smoother

• ILU\_data LU

ILU matrix for ILU smoother.

· INT near kernel dim

dimension of the near kernel for SAMG

REAL \*\* near\_kernel\_basis

basis of near kernel space for SAMG

INT schwarz\_levels

number of levels use schwarz smoother

• Schwarz\_data schwarz

data of Schwarz smoother

· dvector w

Temporary work space.

#### 8.1.1 Detailed Description

Data for AMG solvers.

Note

This is needed for the AMG solver/preconditioner.

Definition at line 628 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

## 8.2 AMG\_data\_bsr Struct Reference

Data for multigrid levels. (BSR format)

```
#include <fasp_block.h>
```

#### **Data Fields**

INT max\_levels

max number of levels

INT num\_levels

number of levels in use <= max\_levels

· dBSRmat A

pointer to the matrix at level level\_num

dBSRmat R

restriction operator at level level\_num

dBSRmat P

prolongation operator at level level\_num

dvector b

pointer to the right-hand side at level level\_num

dvector x

pointer to the iterative solution at level level\_num

dvector diaginv

pointer to the diagonal inverse at level level\_num

dCSRmat Ac

pointer to the matrix at level level\_num (csr format)

dCSRmat PP

pointer to the pressure block (only for reservoir simulation)

• REAL \* pw

pointer to the auxiliary vectors for pressure block

dBSRmat SS

pointer to the saturation block (only for reservoir simulation)

REAL \* sw

pointer to the auxiliary vectors for saturation block

· dvector diaginv SS

pointer to the diagonal inverse of the saturation block at level\_num

• ILU\_data PP\_LU

ILU data for pressure block.

· ivector cfmark

pointer to the CF marker at level level num

· INT ILU levels

number of levels use ILU smoother

• ILU\_data LU

ILU matrix for ILU smoother.

• INT near\_kernel\_dim

dimension of the near kernel for SAMG

• REAL \*\* near kernel basis

basis of near kernel space for SAMG

· dvector w

temporary work space

#### 8.2.1 Detailed Description

Data for multigrid levels. (BSR format)

Note

This structure is needed for the AMG solver/preconditioner in BSR format

Definition at line 191 of file fasp block.h.

The documentation for this struct was generated from the following file:

· fasp block.h

### 8.3 AMG\_param Struct Reference

Parameters for AMG solver.

```
#include <fasp.h>
```

#### **Data Fields**

SHORT AMG\_type

type of AMG method

SHORT print\_level

print level for AMG

INT maxit

max number of iterations of AMG

REAL tol

stopping tolerance for AMG solver

SHORT max\_levels

max number of levels of AMG

· INT coarse dof

max coarsest level dof

SHORT cycle\_type

type of AMG cycle

· SHORT smoother

smoother type

• SHORT smooth\_order

smoother order

SHORT presmooth\_iter

number of presmoothers

SHORT postsmooth\_iter

number of postsmoothers

· REAL relaxation

relaxation parameter for SOR smoother

SHORT polynomial\_degree

degree of the polynomial smoother

· SHORT coarse\_scaling

switch of scaling of the coarse grid correction

SHORT amli\_degree

degree of the polynomial used by AMLI cycle

· REAL \* amli coef

coefficients of the polynomial used by AMLI cycle

SHORT nl\_amli\_krylov\_type

type of krylov method used by Nonlinear AMLI cycle

SHORT coarsening\_type

coarsening type

• SHORT interpolation\_type

interpolation type

· REAL strong\_threshold

strong connection threshold for coarsening

REAL max\_row\_sum

maximal row sum parameter

REAL truncation\_threshold

truncation threshold

INT aggressive\_level

number of levels use aggressive coarsening

INT aggressive\_path

numebr of paths use to determin stongly coupled C points

REAL strong\_coupled

strong coupled threshold for aggregate

• INT max\_aggregation

max size of each aggregate

· REAL tentative smooth

relaxation parameter for smoothing the tentative prolongation

· SHORT smooth\_filter

switch for filtered matrix used for smoothing the tentative prolongation

SHORT ILU\_levels

number of levels use ILU smoother

SHORT ILU\_type

ILU type for smoothing.

INT ILU\_Ifil

level of fill-in for ILUs and ILUk

REAL ILU\_droptol

drop tolerence for ILUt

REAL ILU\_relax

relaxiation for ILUs

· REAL ILU permtol

permuted if permtol\*|a(i,j)| > |a(i,i)|

· INT schwarz levels

number of levels use schwarz smoother

• INT schwarz\_mmsize

maximal block size

INT schwarz\_maxlvl

maximal levels

INT schwarz\_type

type of schwarz method

#### 8.3.1 Detailed Description

Parameters for AMG solver.

Note

This is needed for the AMG solver/preconditioner.

Definition at line 504 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

### 8.4 block\_BSR Struct Reference

Block REAL matrix format for reservoir simulation.

#include <fasp\_block.h>

#### **Data Fields**

dBSRmat ResRes

reservoir-reservoir block

dCSRmat ResWel

reservoir-well block

dCSRmat WelRes

well-reservoir block

dCSRmat WelWel

well-well block

#### 8.4.1 Detailed Description

Block REAL matrix format for reservoir simulation.

Definition at line 165 of file fasp\_block.h.

The documentation for this struct was generated from the following file:

· fasp\_block.h

## 8.5 block\_dCSRmat Struct Reference

Block REAL CSR matrix format.

```
#include <fasp_block.h>
```

#### **Data Fields**

INT brow

row number of blocks in A, m

INT bcol

column number of blocks A, n

dCSRmat \*\* blocks

blocks of dCSRmat, point to blocks[brow][bcol]

#### 8.5.1 Detailed Description

Block REAL CSR matrix format.

Note

The starting index of A is 0.

Definition at line 77 of file fasp\_block.h.

The documentation for this struct was generated from the following file:

• fasp\_block.h

### 8.6 block\_dvector Struct Reference

Block REAL vector structure.

```
#include <fasp_block.h>
```

#### **Data Fields**

• INT brow

row number of blocks in A, m

dvector \*\* blocks

blocks of dvector, point to blocks[brow]

#### 8.6.1 Detailed Description

Block REAL vector structure.

Definition at line 113 of file fasp\_block.h.

The documentation for this struct was generated from the following file:

· fasp\_block.h

## 8.7 block\_iCSRmat Struct Reference

Block INT CSR matrix format.

```
#include <fasp_block.h>
```

#### **Data Fields**

INT brow

row number of blocks in A, m

INT bcol

column number of blocks A, n

iCSRmat \*\* blocks

blocks of iCSRmat, point to blocks[brow][bcol]

#### 8.7.1 Detailed Description

Block INT CSR matrix format.

Note

The starting index of A is 0.

Definition at line 96 of file fasp\_block.h.

The documentation for this struct was generated from the following file:

• fasp\_block.h

## 8.8 block\_ivector Struct Reference

Block INT vector structure.

```
#include <fasp_block.h>
```

#### **Data Fields**

• INT brow

row number of blocks in A, m

ivector \*\* blocks

blocks of dvector, point to blocks[brow]

#### 8.8.1 Detailed Description

Block INT vector structure.

Note

The starting index of A is 0.

Definition at line 129 of file fasp\_block.h.

The documentation for this struct was generated from the following file:

· fasp\_block.h

### 8.9 block\_Reservoir Struct Reference

Block REAL matrix format for reservoir simulation.

```
#include <fasp_block.h>
```

#### **Data Fields**

dSTRmat ResRes

reservoir-reservoir block

dCSRmat ResWel

reservoir-well block

dCSRmat WelRes

well-reservoir block

dCSRmat WelWel

well-well block

#### 8.9.1 Detailed Description

Block REAL matrix format for reservoir simulation.

Definition at line 144 of file fasp\_block.h.

The documentation for this struct was generated from the following file:

· fasp\_block.h

#### 8.10 dBSRmat Struct Reference

Block sparse row storage matrix of REAL type.

```
#include <fasp_block.h>
```

#### **Data Fields**

INT ROW

number of rows of sub-blocks in matrix A, M

INT COL

number of cols of sub-blocks in matrix A, N

INT NNZ

number of nonzero sub-blocks in matrix A, NNZ

• INT nb

dimension of each sub-block

INT storage\_manner

storage manner for each sub-block

- REAL \* val
- INT \* IA

integer array of row pointers, the size is ROW+1

• INT \* JA

#### 8.10.1 Detailed Description

Block sparse row storage matrix of REAL type.

Note

This data structure is adapted from the Intel MKL library. Refer to: http://software.intel.-com/sites/products/documentation/hpc/mkl/lin/index.htm

Some of the following entries are capitalized to stress that they are for blocks!

Definition at line 37 of file fasp\_block.h.

#### 8.10.2 Field Documentation

8.10.2.1 INT\* JA

Element i of the integer array columns is the number of the column in the block matrix that contains the i-th non-zero block. The size is NNZ.

Definition at line 67 of file fasp block.h.

#### 8.10.2.2 **REAL**\* val

A real array that contains the elements of the non-zero blocks of a sparse matrix. The elements are stored block-by-block in row major order. A non-zero block is the block that contains at least one non-zero element. All elements of non-zero blocks are stored, even if some of them is equal to zero. Within each nonzero block elements are stored in row-major order and the size is (NNZ\*nb\*nb).

Definition at line 60 of file fasp\_block.h.

The documentation for this struct was generated from the following file:

· fasp\_block.h

#### 8.11 dCOOmat Struct Reference

Sparse matrix of REAL type in COO (or IJ) format.

```
#include <fasp.h>
```

#### **Data Fields**

INT row

row number of matrix A, m

INT col

column of matrix A, n

• INT nnz

number of nonzero entries

• INT \* I

integer array of row indices, the size is nnz

• INT \* J

integer array of column indices, the size is nnz

• REAL \* val

nonzero entries of A

#### 8.11.1 Detailed Description

Sparse matrix of REAL type in COO (or IJ) format.

Coordinate Format (I,J,A)

Note

The starting index of A is 0.

Definition at line 207 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

#### 8.12 dCSRLmat Struct Reference

Sparse matrix of REAL type in CSRL format.

```
#include <fasp.h>
```

#### **Data Fields**

INT row

number of rows

INT col

number of cols

• INT nnz

number of nonzero entries

• INT dif

number of different values in i-th row, i=0:nrows-1

• INT \* nz\_diff

nz\_diff[i]: the i-th different value in 'nzrow'

• INT \* index

row index of the matrix (length-grouped): rows with same nnz are together

• INT \* start

j in {start[i],...,start[i+1]-1} means nz\_diff[i] nnz in index[j]-row

• INT \* ja

column indices of all the nonzeros

• REAL \* val

values of all the nonzero entries

#### 8.12.1 Detailed Description

Sparse matrix of REAL type in CSRL format.

Definition at line 263 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

#### 8.13 dCSRmat Struct Reference

Sparse matrix of REAL type in CSR format.

```
#include <fasp.h>
```

#### **Data Fields**

• INT row

row number of matrix A, m

INT col

column of matrix A, n

INT nnz

number of nonzero entries

• INT \* IA

integer array of row pointers, the size is m+1

INT \* JA

integer array of column indexes, the size is nnz

REAL \* val

nonzero entries of A

#### 8.13.1 Detailed Description

Sparse matrix of REAL type in CSR format.

CSR Format (IA,JA,A) in REAL

Note

The starting index of A is 0.

Definition at line 147 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

#### 8.14 ddenmat Struct Reference

Dense matrix of REAL type.

```
#include <fasp.h>
```

#### **Data Fields**

• INT row

number of rows

INT col

number of columns

• REAL \*\* val

actual matrix entries

#### 8.14.1 Detailed Description

Dense matrix of REAL type.

A dense REAL matrix

Definition at line 107 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

#### 8.15 dSTRmat Struct Reference

Structure matrix of REAL type.

```
#include <fasp.h>
```

#### **Data Fields**

• INT nx

number of grids in x direction

• INT ny

number of grids in y direction

INT nz

number of grids in z direction

INT nxy

number of grids on x-y plane

INT nc

size of each block (number of components)

INT ngrid

number of grids

• REAL \* diag

diagonal entries (length is  $ngrid*(nc^2)$ )

INT nband

number of off-diag bands

INT \* offsets

offsets of the off-diagals (length is nband)

REAL \*\* offdiag

off-diagonal entries (dimension is nband \* [(ngrid-|offsets|) \* nc $^{\land}$ 2])

#### 8.15.1 Detailed Description

Structure matrix of REAL type.

Note

Every nc<sup>2</sup> entries of the array diag and off-diag[i] store one block: For 2D matrix, the recommended offsets is [-1,1,-nx,nx]; For 3D matrix, the recommended offsets is [-1,1,-nx,nx,-nxy,nxy].

Definition at line 302 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

### 8.16 dvector Struct Reference

Vector with n entries of REAL type.

```
#include <fasp.h>
```

#### **Data Fields**

INT row

number of rows

• REAL \* val

actual vector entries

#### 8.16.1 Detailed Description

Vector with n entries of REAL type.

Definition at line 340 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

### 8.17 grid2d Struct Reference

Two dimensional grid data structure.

```
#include <fasp.h>
```

#### **Data Fields**

- REAL(\* p )[2]
- INT(\* e)[2]
- INT(\* t)[3]
- INT(\* s )[3]
- INT \* pdiri
- INT \* ediri
- INT \* pfather
- INT \* efather
- INT \* tfatherINT vertices
- INT edges
- INT triangles

#### 8.17.1 Detailed Description

Two dimensional grid data structure.

Note

The grid2d structure is simply a list of triangles, edges and vertices. edge i has 2 vertices e[i], triangle i has 3 edges s[i], 3 vertices t[i] vertex i has two coordinates p[i]

Definition at line 1004 of file fasp.h.

8.17.2 Field Documentation

8.17.2.1 **INT**(\* e)[2]

Vertices of edges

Definition at line 1007 of file fasp.h.

8.17.2.2 INT edges

Number of edges

Definition at line 1018 of file fasp.h.

8.17.2.3 INT\* ediri

Boundary flags (0 <=> interior edge)

Definition at line 1011 of file fasp.h.

8.17.2.4 **INT**\* efather

Father edge or triangle

Definition at line 1014 of file fasp.h.

8.17.2.5 **REAL**(\* p)[2]

Coordinates of vertices

Definition at line 1006 of file fasp.h.

8.17.2.6 INT\* pdiri

Boundary flags (0 <=> interior point)

Definition at line 1010 of file fasp.h.

8.17.2.7 **INT**\* pfather

Father point or edge

Definition at line 1013 of file fasp.h.

8.17.2.8 **INT**(\* s)[3]

Edges of triangles

Definition at line 1009 of file fasp.h.

8.17.2.9 INT(\* t)[3]

Vertices of triangles

Definition at line 1008 of file fasp.h.

8.17.2.10 INT\* tfather

Father triangle

Definition at line 1015 of file fasp.h.

8.17.2.11 **INT** triangles

Number of triangles

Definition at line 1019 of file fasp.h.

8.17.2.12 INT vertices

Number of grid points

Definition at line 1017 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

#### 8.18 iCOOmat Struct Reference

Sparse matrix of INT type in COO (or IJ) format.

```
#include <fasp.h>
```

#### **Data Fields**

INT row

row number of matrix A, m

INT col

column of matrix A, n

• INT nnz

number of nonzero entries

• INT \* I

integer array of row indices, the size is nnz

• INT \* J

integer array of column indices, the size is nnz

INT \* val

nonzero entries of A

#### 8.18.1 Detailed Description

Sparse matrix of INT type in COO (or IJ) format.

Coordinate Format (I,J,A)

Note

The starting index of A is 0.

Definition at line 237 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

#### 8.19 iCSRmat Struct Reference

Sparse matrix of INT type in CSR format.

```
#include <fasp.h>
```

#### **Data Fields**

INT row

row number of matrix A, m

INT col

column of matrix A, n

INT nnz

number of nonzero entries

• INT \* IA

integer array of row pointers, the size is m+1

• INT \* JA

integer array of column indexes, the size is nnz

• INT \* val

nonzero entries of A

#### 8.19.1 Detailed Description

Sparse matrix of INT type in CSR format.

CSR Format (IA,JA,A) in integer

Note

The starting index of A is 0.

Definition at line 177 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

#### 8.20 idenmat Struct Reference

#### Dense matrix of INT type.

```
#include <fasp.h>
```

#### **Data Fields**

INT row

number of rows

INT col

number of columns

INT \*\* val

actual matrix entries

### 8.20.1 Detailed Description

Dense matrix of INT type.

A dense INT matrix

Definition at line 126 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

## 8.21 ILU\_data Struct Reference

#### Data for ILU setup.

```
#include <fasp.h>
```

#### **Data Fields**

INT row

row number of matrix LU, m

• INT col

column of matrix LU, n

• INT nzlu

number of nonzero entries

• INT \* ijlu

integer array of row pointers and column indexes, the size is nzlu

• REAL \* luval

nonzero entries of LU

• INT nb

block size for BSR type only

• INT nwork

work space size

REAL \* work

work space

# 8.21.1 Detailed Description

Data for ILU setup.

Definition at line 398 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

# 8.22 ILU\_param Struct Reference

#### Parameters for ILU.

```
#include <fasp.h>
```

## **Data Fields**

SHORT print\_level

print leve

SHORT ILU\_type

ILU type for decomposition.

• INT ILU Ifil

level of fill-in for ILUk

• REAL ILU\_droptol

drop tolerence for ILUt

• REAL ILU\_relax

add the sum of dropped elements to diagnal element in proportion relax

REAL ILU\_permtol

```
permuted if permtol*|a(i,j)| > |a(i,i)|
```

# 8.22.1 Detailed Description

Parameters for ILU.

Definition at line 372 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

# 8.23 input\_param Struct Reference

Input parameters.

```
#include <fasp.h>
```

## **Data Fields**

- SHORT print\_level
- SHORT output\_type
- char workdir [256]
- INT problem\_num
- SHORT solver\_type
- SHORT precond\_type
- SHORT stop\_type
- · REAL itsolver tol
- · INT itsolver maxit
- INT restart
- SHORT ILU\_type
- INT ILU Ifil
- · REAL ILU droptol
- REAL ILU relax
- REAL ILU permtol
- INT Schwarz\_mmsize
- INT Schwarz maxlvl
- INT Schwarz\_type
- SHORT AMG type
- SHORT AMG\_levels
- SHORT AMG\_cycle\_type
- SHORT AMG\_smoother
- SHORT AMG\_smooth\_order
- REAL AMG\_relaxation
- SHORT AMG polynomial degree
- SHORT AMG\_presmooth\_iter
- SHORT AMG\_postsmooth\_iter
- INT AMG\_coarse\_dof
- REAL AMG\_tol
- INT AMG maxit
- SHORT AMG\_ILU\_levels
- SHORT AMG\_coarse\_scaling
- SHORT AMG\_amli\_degree
- SHORT AMG\_nl\_amli\_krylov\_type
- INT AMG\_schwarz\_levels
- SHORT AMG\_coarsening\_type
- SHORT AMG\_interpolation\_type
- REAL AMG\_strong\_threshold
- REAL AMG\_truncation\_threshold
- REAL AMG\_max\_row\_sum
- INT AMG\_aggressive\_level
- INT AMG\_aggressive\_path
- REAL AMG\_strong\_coupled
- INT AMG\_max\_aggregation
- REAL AMG\_tentative\_smooth
- SHORT AMG\_smooth\_filter

# 8.23.1 Detailed Description

Input parameters.

Input parameters, reading from disk file

Definition at line 912 of file fasp.h.

## 8.23.2 Field Documentation

8.23.2.1 INT AMG\_aggressive\_level

number of levels use aggressive coarsening

Definition at line 967 of file fasp.h.

8.23.2.2 INT AMG\_aggressive\_path

number of paths used to determine strongly coupled C-set

Definition at line 968 of file fasp.h.

8.23.2.3 SHORT AMG\_amli\_degree

degree of the polynomial used by AMLI cycle

Definition at line 957 of file fasp.h.

8.23.2.4 INT AMG\_coarse\_dof

minimal coarsest level dof

Definition at line 952 of file fasp.h.

8.23.2.5 SHORT AMG\_coarse\_scaling

switch of scaling of the coarse grid correction

Definition at line 956 of file fasp.h.

8.23.2.6 SHORT AMG\_coarsening\_type

coarsening type

Definition at line 962 of file fasp.h.

8.23.2.7 SHORT AMG\_cycle\_type

type of cycle

Definition at line 945 of file fasp.h.

8.23.2.8 SHORT AMG\_ILU\_levels

how many levels use ILU smoother

Definition at line 955 of file fasp.h.

8.23.2.9 SHORT AMG\_interpolation\_type

interpolation type

Definition at line 963 of file fasp.h.

8.23.2.10 SHORT AMG\_levels

maximal number of levels

Definition at line 944 of file fasp.h.

8.23.2.11 INT AMG\_max\_aggregation

max size of each aggregate

Definition at line 972 of file fasp.h.

8.23.2.12 REAL AMG\_max\_row\_sum

maximal row sum

Definition at line 966 of file fasp.h.

8.23.2.13 **INT AMG\_maxit** 

number of iterations for AMG used as preconditioner

Definition at line 954 of file fasp.h.

8.23.2.14 SHORT AMG\_nl\_amli\_krylov\_type

type of krylov method used by nonlinear AMLI cycle

Definition at line 958 of file fasp.h.

8.23.2.15 SHORT AMG\_polynomial\_degree

degree of the polynomial smoother

Definition at line 949 of file fasp.h.

8.23.2.16 SHORT AMG\_postsmooth\_iter

number of postsmoothing

Definition at line 951 of file fasp.h.

8.23.2.17 SHORT AMG\_presmooth\_iter

number of presmoothing

Definition at line 950 of file fasp.h.

8.23.2.18 **REAL AMG\_relaxation** 

over-relaxation parameter for SOR

Definition at line 948 of file fasp.h.

8.23.2.19 INT AMG\_schwarz\_levels

number of levels use schwarz smoother

Definition at line 959 of file fasp.h.

8.23.2.20 SHORT AMG\_smooth\_filter

use filterfor smoothing the tentative prolongation or not

Definition at line 974 of file fasp.h.

8.23.2.21 SHORT AMG\_smooth\_order

order for smoothers

Definition at line 947 of file fasp.h.

8.23.2.22 SHORT AMG\_smoother

type of smoother

Definition at line 946 of file fasp.h.

8.23.2.23 REAL AMG\_strong\_coupled

strong coupled threshold for aggregate

Definition at line 971 of file fasp.h.

8.23.2.24 REAL AMG\_strong\_threshold

strong threshold for coarsening

Definition at line 964 of file fasp.h.

8.23.2.25 REAL AMG\_tentative\_smooth

relaxation factor for smoothing the tentative prolongation

Definition at line 973 of file fasp.h.

8.23.2.26 **REAL AMG\_tol** 

tolerance for AMG if used as preconditioner

Definition at line 953 of file fasp.h.

8.23.2.27 REAL AMG\_truncation\_threshold

truncation factor for interpolation

Definition at line 965 of file fasp.h.

8.23.2.28 SHORT AMG\_type

Type of AMG

Definition at line 943 of file fasp.h.

8.23.2.29 REAL ILU\_droptol

drop tolerance

Definition at line 933 of file fasp.h.

8.23.2.30 INT ILU\_IfiI

level of fill-in

Definition at line 932 of file fasp.h.

8.23.2.31 REAL ILU\_permtol

permutation tolerance

Definition at line 935 of file fasp.h.

8.23.2.32 REAL ILU\_relax

scaling factor: add the sum of dropped entries to diagnal

Definition at line 934 of file fasp.h.

8.23.2.33 SHORT ILU\_type

ILU type for decomposition

Definition at line 931 of file fasp.h.

8.23.2.34 INT itsolver\_maxit

maximal number of iterations for iterative solvers

Definition at line 927 of file fasp.h.

8.23.2.35 REAL itsolver\_tol

tolerance for iterative linear solver

Definition at line 926 of file fasp.h.

8.23.2.36 SHORT output\_type

type of output stream

Definition at line 916 of file fasp.h.

8.23.2.37 SHORT precond\_type

type of preconditioner for iterative solvers

Definition at line 924 of file fasp.h.

8.23.2.38 SHORT print\_level

print level

Definition at line 915 of file fasp.h.

8.23.2.39 INT problem\_num

problem number to solve

Definition at line 920 of file fasp.h.

8.23.2.40 INT restart

restart number used in GMRES

Definition at line 928 of file fasp.h.

8.23.2.41 INT Schwarz\_maxlvl

maximal levels

Definition at line 939 of file fasp.h.

8.23.2.42 INT Schwarz\_mmsize

maximal block size

Definition at line 938 of file fasp.h.

8.23.2.43 INT Schwarz\_type

type of schwarz method

Definition at line 940 of file fasp.h.

8.23.2.44 SHORT solver\_type

type of iterative solvers

Definition at line 923 of file fasp.h.

8.23.2.45 SHORT stop\_type

type of stopping criteria for iterative solvers

Definition at line 925 of file fasp.h.

8.23.2.46 char workdir[256]

working directory for data files

Definition at line 919 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

# 8.24 itsolver\_param Struct Reference

Parameters passed to iterative solvers.

#include <fasp.h>

# **Data Fields**

- SHORT itsolver\_type
- SHORT precond\_type
- SHORT stop\_type
- INT maxit
- · REAL tol
- INT restart
- SHORT print\_level

## 8.24.1 Detailed Description

Parameters passed to iterative solvers.

Definition at line 982 of file fasp.h.

## 8.24.2 Field Documentation

8.24.2.1 SHORT itsolver\_type

solver type: see message.h

Definition at line 984 of file fasp.h.

8.24.2.2 INT maxit

max number of iterations

Definition at line 987 of file fasp.h.

8.24.2.3 SHORT precond\_type

preconditioner type: see message.h

Definition at line 985 of file fasp.h.

8.24.2.4 SHORT print\_level

print level: 0-10

Definition at line 990 of file fasp.h.

8.24.2.5 INT restart

number of steps for restarting: for GMRES etc

Definition at line 989 of file fasp.h.

8.24.2.6 SHORT stop\_type

stopping criteria type

Definition at line 986 of file fasp.h.

8.24.2.7 **REAL** tol

convergence tolerance

Definition at line 988 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

# 8.25 ivector Struct Reference

Vector with n entries of INT type.

#include <fasp.h>

## **Data Fields**

• INT row

number of rows

• INT \* val

actual vector entries

# 8.25.1 Detailed Description

Vector with n entries of INT type.

Definition at line 354 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

# 8.26 Link Struct Reference

## Struct for Links.

```
#include <fasp.h>
```

#### **Data Fields**

INT prev

previous node in the linklist

INT next

next node in the linklist

# 8.26.1 Detailed Description

Struct for Links.

Definition at line 1031 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

# 8.27 linked\_list Struct Reference

## A linked list node.

```
#include <fasp.h>
```

## **Data Fields**

• INT data

data

INT head

starting of the list

INT tail

ending of the list

• struct linked\_list \* next\_node

next node

struct linked\_list \* prev\_node

previous node

# 8.27.1 Detailed Description

A linked list node.

Note

This definition is adapted from hypre 2.0.

Definition at line 1048 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

# 8.28 mxv\_matfree Struct Reference

Matrix-vector multiplication, replace the actual matrix.

```
#include <fasp.h>
```

## **Data Fields**

```
    void * data
        data for MxV, can be a Matrix or something else
    void(* fct )(void *, REAL *, REAL *)
        action for MxV, void function pointer
```

## 8.28.1 Detailed Description

Matrix-vector multiplication, replace the actual matrix.

Definition at line 896 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

# 8.29 precond Struct Reference

Preconditioner data and action.

```
#include <fasp.h>
```

## **Data Fields**

```
    void * data
        data for preconditioner, void pointer
    void(* fct )(REAL *, REAL *, void *)
        action for preconditioner, void function pointer
```

# 8.29.1 Detailed Description

Preconditioner data and action.

Note

This is the preconditioner structure for preconditioned iterative methods.

Definition at line 877 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

# 8.30 precond\_block\_data Struct Reference

Data passed to the preconditioner for block diagonal preconditioning.

```
#include <fasp_block.h>
```

## **Data Fields**

- dCSRmat \* A
- dvector \* r
- dCSRmat \*\* Ablock
- ivector \*\* row idx
- ivector \*\* col\_idx
- AMG\_param \* amgparam
- dCSRmat \*\* Aarray

# 8.30.1 Detailed Description

Data passed to the preconditioner for block diagonal preconditioning.

Note

This is needed for the diagnoal block preconditioner.

Definition at line 460 of file fasp\_block.h.

#### 8.30.2 Field Documentation

8.30.2.1 dCSRmat\* A

problem data, the sparse matrix

Definition at line 462 of file fasp\_block.h.

8.30.2.2 dCSRmat\*\* Aarray

data generated in the setup phase

Definition at line 470 of file fasp block.h.

8.30.2.3 dCSRmat\*\* Ablock

problem data, the blocks

Definition at line 465 of file fasp\_block.h.

8.30.2.4 AMG\_param \* amgparam

parameters for AMG

Definition at line 469 of file fasp\_block.h.

8.30.2.5 ivector\*\* col\_idx

problem data, col indices

Definition at line 467 of file fasp block.h.

8.30.2.6 dvector\* r

problem data, the right-hand side vector

Definition at line 463 of file fasp\_block.h.

8.30.2.7 ivector\*\* row\_idx

problem data, row indices

Definition at line 466 of file fasp\_block.h.

The documentation for this struct was generated from the following file:

• fasp\_block.h

# 8.31 precond\_block\_reservoir\_data Struct Reference

Data passed to the preconditioner for preconditioning reservoir simulation problems.

#include <fasp\_block.h>

## **Data Fields**

• block\_Reservoir \* A

problem data in block\_Reservoir format

block\_dCSRmat \* Abcsr

problem data in block\_dCSRmat format

dCSRmat \* Acsr

problem data in CSR format

INT ILU\_Ifil

level of fill-in for structured ILU(k)

dSTRmat \* LU

LU matrix for Reservoir-Reservoir block in STR format.

ILU data \* LUcsr

LU matrix for Reservoir-Reservoir block in CSR format.

• AMG\_data \* mgl\_data

AMG data for presure-presure block.

SHORT print level

print level in AMG preconditioner

INT maxit AMG

max number of iterations of AMG preconditioner

SHORT max levels

max number of AMG levels

· REAL amg tol

tolerance for AMG preconditioner

SHORT cycle\_type

AMG cycle type.

SHORT smoother

AMG smoother type.

SHORT presmooth\_iter

number of presmoothing

· SHORT postsmooth\_iter

number of postsmoothing

SHORT coarsening\_type

coarsening type

· REAL relaxation

relaxation parameter for SOR smoother

· SHORT coarse scaling

switch of scaling of coarse grid correction

INT maxit

max number of iterations

· INT restart

number of iterations for restart

REAL tol

tolerance for convergence

• REAL \* invS

inverse of the schur complement (-I - Awr\*Arr $^{\setminus}$ {-1}\*Arw) $^{\wedge}$ {-1}, Arr may be replaced by LU

dvector \* DPSinvDSS

Diag(PS) \* inv(Diag(SS))

- SHORT scaled
- · ivector \* perf\_idx
- dSTRmat \* RR
- dCSRmat \* WW
- dCSRmat \* PP
- dSTRmat \* SS
- precond\_diagstr \* diag
- dvector \* diaginv
- ivector \* pivot
- dvector \* diaginvS
- ivector \* pivotS
- · ivector \* order
- · dvector r
- REAL \* w

## 8.31.1 Detailed Description

Data passed to the preconditioner for preconditioning reservoir simulation problems.

Note

This is only needed for the Black Oil model with wells

Definition at line 361 of file fasp block.h.

8.31.2 Field Documentation

8.31.2.1 precond\_diagstr\* diag

the diagonal inverse for diagonal scaling

Definition at line 441 of file fasp\_block.h.

8.31.2.2 dvector\* diaginv

the inverse of the diagonals for GS/block GS smoother (whole reservoir matrix)

Definition at line 442 of file fasp\_block.h.

8.31.2.3 dvector\* diaginv\$

the inverse of the diagonals for GS/block GS smoother (saturation block)

Definition at line 444 of file fasp\_block.h.

8.31.2.4 ivector\* order

order for smoothing

Definition at line 446 of file fasp\_block.h.

8.31.2.5 ivector\* perf\_idx

variable index for perf

Definition at line 434 of file fasp\_block.h.

8.31.2.6 ivector\* pivot

the pivot for the GS/block GS smoother (whole reservoir matrix)

Definition at line 443 of file fasp\_block.h.

8.31.2.7 ivector\* pivotS

the pivot for the GS/block GS smoother (saturation block)

Definition at line 445 of file fasp block.h.

8.31.2.8 dCSRmat\* PP

pressure block after diagonal scaling

Definition at line 438 of file fasp\_block.h.

8.31.2.9 dvector r

temporary dvector used to store and restore the residual

Definition at line 449 of file fasp\_block.h.

8.31.2.10 dSTRmat\* RR

Diagonal scaled reservoir block

Definition at line 436 of file fasp\_block.h.

8.31.2.11 SHORT scaled

whether the matirx is scaled

Definition at line 433 of file fasp block.h.

8.31.2.12 dSTRmat\* SS

saturation block after diaogonal scaling

Definition at line 439 of file fasp\_block.h.

8.31.2.13 REAL\* w

temporary work space for other usage

Definition at line 450 of file fasp\_block.h.

8.31.2.14 dCSRmat\* WW

Argumented well block

Definition at line 437 of file fasp\_block.h.

The documentation for this struct was generated from the following file:

fasp\_block.h

# 8.32 precond\_data Struct Reference

Data passed to the preconditioners.

#include <fasp.h>

## **Data Fields**

SHORT AMG\_type

type of AMG method

SHORT print level

print level in AMG preconditioner

INT maxit

max number of iterations of AMG preconditioner

SHORT max levels

max number of AMG levels

· REAL tol

tolerance for AMG preconditioner

SHORT cycle\_type

AMG cycle type.

· SHORT smoother

AMG smoother type.

SHORT smooth\_order

AMG smoother ordering.

SHORT presmooth\_iter

number of presmoothing

SHORT postsmooth\_iter

number of postsmoothing

· REAL relaxation

coarsening type

SHORT polynomial\_degree

degree of the polynomial smoother

• SHORT coarsening\_type

switch of scaling of the coarse grid correction

SHORT coarse\_scaling

relaxation parameter for SOR smoother

SHORT amli\_degree

degree of the polynomial used by AMLI cycle

• SHORT nl\_amli\_krylov\_type

type of krylov method used by Nonlinear AMLI cycle

· REAL tentative\_smooth

smooth factor for smoothing the tentative prolongation

REAL \* amli\_coef

coefficients of the polynomial used by AMLI cycle

• AMG\_data \* mgl\_data

AMG preconditioner data.

• ILU data \* LU

ILU preconditioner data (needed for CPR type preconditioner)

dCSRmat \* A

Matrix data.

· dvector r

temporary dvector used to store and restore the residual

REAL \* w

temporary work space for other usage

# 8.32.1 Detailed Description

Data passed to the preconditioners.

Definition at line 689 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

# 8.33 precond\_data\_bsr Struct Reference

Data passed to the preconditioners.

```
#include <fasp_block.h>
```

## **Data Fields**

SHORT AMG\_type

type of AMG method

SHORT print\_level

print level in AMG preconditioner

INT maxit

max number of iterations of AMG preconditioner

INT max levels

max number of AMG levels

· REAL tol

tolerance for AMG preconditioner

SHORT cycle\_type

AMG cycle type.

SHORT smoother

AMG smoother type.

SHORT smooth\_order

AMG smoother ordering.

SHORT presmooth\_iter

number of presmoothing

SHORT postsmooth\_iter

number of postsmoothing

SHORT coarsening\_type

coarsening type

· REAL relaxation

relaxation parameter for SOR smoother

• SHORT coarse\_scaling

switch of scaling of the coarse grid correction

SHORT amli\_degree

degree of the polynomial used by AMLI cycle

• REAL \* amli\_coef

coefficients of the polynomial used by AMLI cycle

· REAL tentative\_smooth

smooth factor for smoothing the tentative prolongation

SHORT nl\_amli\_krylov\_type

type of krylov method used by Nonlinear AMLI cycle

AMG data bsr \* mgl data

AMG preconditioner data.

AMG\_data \* pres\_mgl\_data

AMG preconditioner data for pressure block.

ILU data \* LU

ILU preconditioner data (needed for CPR type preconditioner)

dBSRmat \* A

Matrix data.

dvector r

temporary dvector used to store and restore the residual

• REAL \* w

temporary work space for other usage

# 8.33.1 Detailed Description

Data passed to the preconditioners.

Note

This structure is needed for the AMG solver/preconditioner in BSR format

Definition at line 282 of file fasp block.h.

The documentation for this struct was generated from the following file:

· fasp\_block.h

# 8.34 precond\_data\_str Struct Reference

Data passed to the preconditioner for dSTRmat matrices.

```
#include <fasp.h>
```

## **Data Fields**

SHORT AMG type

type of AMG method

SHORT print\_level

print level in AMG preconditioner

INT maxit

max number of iterations of AMG preconditioner

SHORT max\_levels

max number of AMG levels

REAL tol

tolerance for AMG preconditioner

SHORT cycle\_type

AMG cycle type.

SHORT smoother

AMG smoother type.

· SHORT presmooth\_iter

number of presmoothing

SHORT postsmooth\_iter

number of postsmoothing

SHORT coarsening\_type

coarsening type

· REAL relaxation

relaxation parameter for SOR smoother

· SHORT coarse\_scaling

switch of scaling of the coarse grid correction

AMG\_data \* mgl\_data

AMG preconditioner data.

• ILU\_data \* LU

ILU preconditioner data (needed for CPR type preconditioner)

SHORT scaled

whether the matrx are scaled or not

dCSRmat \* A

the orginal CSR matrix

dSTRmat \* A\_str

stor the whole reservoir block in STR format

dSTRmat \* SS\_str

store Saturation block in STR format

dvector \* diaginv

the inverse of the diagonals for GS/block GS smoother (whole reservoir matrix)

ivector \* pivot

the pivot for the GS/block GS smoother (whole reservoir matrix)

dvector \* diaginvS

the inverse of the diagonals for GS/block GS smoother (saturation block)

ivector \* pivotS

the pivot for the GS/block GS smoother (saturation block)

· ivector \* order

order for smoothing

ivector \* neigh

arrary to store neighbor information

• dvector r

temporary dvector used to store and restore the residual

• REAL \* w

temporary work space for other usage

# 8.34.1 Detailed Description

Data passed to the preconditioner for dSTRmat matrices.

Definition at line 768 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

# 8.35 precond\_diagbsr Struct Reference

Data passed to diagnal preconditioner for dBSRmat matrices.

```
#include <fasp_block.h>
```

#### **Data Fields**

• INT nb

dimension of each sub-block

· dvector diag

diagnal elements

# 8.35.1 Detailed Description

Data passed to diagnal preconditioner for dBSRmat matrices.

Note

This is needed for the diagnal preconditioner.

Definition at line 264 of file fasp\_block.h.

The documentation for this struct was generated from the following file:

• fasp\_block.h

# 8.36 precond\_diagstr Struct Reference

Data passed to diagnal preconditioner for dSTRmat matrices.

```
#include <fasp.h>
```

# **Data Fields**

• INT nc

number of components

· dvector diag

diagnal elements

# 8.36.1 Detailed Description

Data passed to diagnal preconditioner for dSTRmat matrices.

Note

This is needed for the diagnal preconditioner.

Definition at line 861 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

# 8.37 precond\_FASP\_blkoil\_data Struct Reference

Data passed to the preconditioner for preconditioning reservoir simulation problems.

```
#include <fasp_block.h>
```

## **Data Fields**

• block BSR \* A

Part 1: Basic data.

SHORT scaled

Part 2: Data for CPR-like preconditioner for reservoir block.

- dvector \* diaginv\_noscale
- dBSRmat \* RR
- ivector \* neigh
- ivector \* order
- dBSRmat \* SS
- dvector \* diaginv\_S
- ivector \* pivot\_S
- dCSRmat \* PP
- AMG\_data \* mgl\_data
- SHORT print\_level

print level in AMG preconditioner

INT maxit\_AMG

max number of iterations of AMG preconditioner

SHORT max\_levels

max number of AMG levels

REAL amg\_tol

tolerance for AMG preconditioner

SHORT cycle\_type

AMG cycle type.

SHORT smoother

AMG smoother type.

• SHORT smooth\_order

AMG smoothing order.

· SHORT presmooth\_iter

number of presmoothing

· SHORT postsmooth\_iter

number of postsmoothing

• SHORT coarsening\_type

coarsening type

REAL relaxation

relaxation parameter for SOR smoother

SHORT coarse scaling

switch of scaling of coarse grid correction

SHORT amli\_degree

degree of the polynomial used by AMLI cycle

• REAL \* amli\_coef

coefficients of the polynomial used by AMLI cycle

· REAL tentative\_smooth

relaxation parameter for smoothing the tentative prolongation

- · dvector \* diaginv
- ivector \* pivot
- ILU data \* LU

data of ILU for reservoir block

- ivector \* perf\_idx
- ivector \* perf\_neigh
- dCSRmat \* WW
- void \* Numeric

data for direct solver for argumented well block

• REAL \* invS

inverse of the schur complement (-I - Awr\*Arr^{-1}\*Arw)^{-1}, Arr may be replaced by LU

- INT maxit
- INT restart
- REAL tol
- dvector r
- REAL \* w

## 8.37.1 Detailed Description

Data passed to the preconditioner for preconditioning reservoir simulation problems.

Note

This is only needed for the Black Oil model with wells

Definition at line 480 of file fasp\_block.h.

# 8.37.2 Field Documentation

8.37.2.1 block\_BSR\* A

Part 1: Basic data.

whole jacobian system in block\_BSRmat

Definition at line 485 of file fasp block.h.

8.37.2.2 dvector\* diaginv

inverse of the diagonal blocks of reservoir block

Definition at line 554 of file fasp\_block.h.

8.37.2.3 dvector\* diaginv\_noscale

inverse of diagonal blocks for diagonal scaling

Definition at line 492 of file fasp\_block.h.

8.37.2.4 dvector\* diaginv\_S

inverse of the diagonal blocks of saturation block

Definition at line 501 of file fasp\_block.h.

8.37.2.5 INT maxit

max number of iterations

Definition at line 572 of file fasp\_block.h.

8.37.2.6 AMG\_data\* mgl\_data

AMG data for presure-presure block

Definition at line 506 of file fasp\_block.h.

8.37.2.7 ivector\* neigh

neighbor information of the reservoir block

Definition at line 496 of file fasp\_block.h.

8.37.2.8 ivector\* order

ordering of the reservoir block

Definition at line 497 of file fasp\_block.h.

8.37.2.9 ivector\* perf\_idx

index of blocks which have perforation

Definition at line 561 of file fasp\_block.h.

8.37.2.10 ivector\* perf\_neigh

index of blocks which are neighbors of perforations (include perforations)

Definition at line 562 of file fasp\_block.h.

8.37.2.11 ivector\* pivot

pivot for the GS smoothers for the reservoir matrix

Definition at line 555 of file fasp\_block.h.

8.37.2.12 ivector\* pivot\_S

pivoting for the GS smoothers for saturation block

Definition at line 502 of file fasp\_block.h.

8.37.2.13 dCSRmat\* PP

pressure block

Definition at line 505 of file fasp block.h.

8.37.2.14 dvector r

temporary dvector used to store and restore the residual

Definition at line 577 of file fasp\_block.h.

8.37.2.15 INT restart

number of iterations for restart

Definition at line 573 of file fasp\_block.h.

8.37.2.16 dBSRmat\* RR

reservoir block

Definition at line 493 of file fasp block.h.

8.37.2.17 SHORT scaled

Part 2: Data for CPR-like preconditioner for reservoir block.

scaled = 1 means the the following RR block is diagonal scaled

Definition at line 491 of file fasp\_block.h.

8.37.2.18 dBSRmat\* SS

saturation block

Definition at line 500 of file fasp\_block.h.

8.37.2.19 REAL tol

tolerance

Definition at line 574 of file fasp\_block.h.

8.37.2.20 REAL\* w

temporary work space for other usage

Definition at line 578 of file fasp\_block.h.

8.37.2.21 dCSRmat\* WW

Argumented well block

Definition at line 563 of file fasp\_block.h.

The documentation for this struct was generated from the following file:

• fasp\_block.h

# 8.38 Schwarz\_data Struct Reference

Data for Schwarz methods.

#include <fasp.h>

## **Data Fields**

dCSRmat A

pointer to the matrix

• INT nblk

number of blocks

• INT \* iblock

row index of blocks

• INT \* jblock

column index of blocks

REAL \* rhsloc

local right hand side

• REAL \* au

LU decomposition: the U block.

• REAL \* al

LU decomposition: the L block.

• INT schwarz\_type

Schwarz method type.

INT memt

working space size

INT \* mask

mask

• INT \* maxa

maxa

## 8.38.1 Detailed Description

Data for Schwarz methods.

This is needed for the schwarz solver, preconditioner/smoother.

Definition at line 457 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

# 8.39 Schwarz\_param Struct Reference

Parameters for Schwarz method.

```
#include <fasp.h>
```

## **Data Fields**

SHORT print\_level

print leve

SHORT schwarz\_type

type for Schwarz method

INT schwarz maxlvl

maximal level for constructing the blocks

• INT schwarz\_mmsize

maxiaml size of blocks

## 8.39.1 Detailed Description

Parameters for Schwarz method.

Added on 05/14/2012

Definition at line 433 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

Data	Structure	Daa	
บลเล	STRUCTURE	. Docum	entation

# **Chapter 9**

# **File Documentation**

# 9.1 amg.c File Reference

AMG method as an iterative solver (main file)

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

• void fasp\_solver\_amg (dCSRmat \*A, dvector \*b, dvector \*x, AMG\_param \*param)

Solve Ax = b by algebaric multigrid methods.

# 9.1.1 Detailed Description

AMG method as an iterative solver (main file)

Definition in file amg.c.

## 9.1.2 Function Documentation

```
9.1.2.1 void fasp_solver_amg ( dCSRmat * A, dvector * b, dvector * x, AMG_param * param )
```

Solve Ax = b by algebraic multigrid methods.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
Х	Pointer to dvector: the unknowns

66 File Documentation

param Pointer to AMG\_param: AMG parameters

**Author** 

Chensong Zhang

Date

04/06/2010

Note

Refer to "Multigrid" by U. Trottenberg, C. W. Oosterlee and A. Schuller Appendix A.7 (by A. Brandt, P. Oswald and K. Stuben) Academic Press Inc., San Diego, CA, 2001.

Modified by Chensong Zhang on 01/10/2012 Modified by Chensong Zhang on 05/05/2013: Remove error handling from AMG setup

Definition at line 37 of file amg.c.

# 9.2 amg\_setup\_aggregation\_bsr.inl File Reference

Utilies for multigrid cycles in BSR format.

## 9.2.1 Detailed Description

Utilies for multigrid cycles in BSR format.

Definition in file amg\_setup\_aggregation\_bsr.inl.

# 9.3 amg\_setup\_aggregation\_csr.inl File Reference

Utilies for multigrid cycles for CSR matrices.

## 9.3.1 Detailed Description

Utilies for multigrid cycles for CSR matrices.

Definition in file amg\_setup\_aggregation\_csr.inl.

# 9.4 amg\_setup\_cr.c File Reference

Brannick-Falgout compatible relaxation based AMG: SETUP phase.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

SHORT fasp\_amg\_setup\_cr (AMG\_data \*mgl, AMG\_param \*param)
 Set up phase of Brannick Falgout CR coarsening for classic AMG.

## 9.4.1 Detailed Description

Brannick-Falgout compatible relaxation based AMG: SETUP phase.

Note

Setup A, P, R and levels using the Compatible Relaxation coarsening for classic AMG interpolation Refer to J. Brannick and R. Falgout "Compatible relaxation and coarsening in AMG"

TODO: Not working. Yet need to be fixed. -Chensong

Definition in file amg\_setup\_cr.c.

#### 9.4.2 Function Documentation

```
9.4.2.1 SHORT fasp_amg_setup_cr ( AMG data * mgl, AMG param * param )
```

Set up phase of Brannick Falgout CR coarsening for classic AMG.

#### **Parameters**

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

# Returns

SUCCESS if successed, otherwise, error information.

# Author

James Brannick

Date

04/21/2010

Modified by Chensong Zhang on 05/10/2013: adjust the structure.

Definition at line 38 of file amg\_setup\_cr.c.

# 9.5 amg\_setup\_rs.c File Reference

Ruge-Stuben AMG: SETUP phase.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

68 File Documentation

## **Functions**

INT fasp\_amg\_setup\_rs (AMG\_data \*mgl, AMG\_param \*param)

Setup phase of Ruge and Stuben's classic AMG.

INT fasp amg setup rs omp (AMG data \*mgl, AMG param \*param)

Setup of AMG based on R-S coarsening.

## 9.5.1 Detailed Description

Ruge-Stuben AMG: SETUP phase.

Note

Setup A, P, R, levels using classic AMG! Refter to "Multigrid" by Stuben in U. Trottenberg, C. W. Oosterlee and A. Schuller. Appendix A.7 (by A. Brandt, P. Oswald and K. Stuben). Academic Press Inc., San Diego, CA, 2001.

Definition in file amg\_setup\_rs.c.

#### 9.5.2 Function Documentation

9.5.2.1 INT fasp\_amg\_setup\_rs ( AMG\_data \* mgl, AMG\_param \* param )

Setup phase of Ruge and Stuben's classic AMG.

#### **Parameters**

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

#### Returns

SUCCESS if successed, otherwise, error information.

#### **Author**

Chensong Zhang

Date

05/09/2010

Modified by Chensong Zhang on 04/04/2009. Modified by Chensong Zhang on 05/09/2010. Modified by Zhiyang Zhou on 11/17/2010. Modified by Xiaozhe Hu on 01/23/2011: add AMLI cycle. Modified by Chensong zhang on 09/09/2011: add min dof. Modified by Xiaozhe Hu on 04/24/2013: aggressive coarsening. Modified by Chensong Zhang on 05/03/2013: add error handling in setup. Modified by Chensong Zhang on 05/10/2013: adjust the structure.

Definition at line 47 of file amg\_setup\_rs.c.

9.5.2.2 INT fasp\_amg\_setup\_rs\_omp ( AMG\_data \* mgl, AMG\_param \* param )

Setup of AMG based on R-S coarsening.

#### **Parameters**

mgl	Pointer to AMG_data data
param	Pointer to AMG parameters

#### Returns

SUCCESS if successed, otherwise, error information.

#### **Author**

Chunsheng Feng, Xiaoqiang Yue

Date

03/11/2011

Definition at line 253 of file amg\_setup\_rs.c.

# 9.6 amg\_setup\_sa.c File Reference

Smoothed aggregation AMG: SETUP phase.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "amg_setup_aggregation_csr.inl"
```

## **Functions**

SHORT fasp\_amg\_setup\_sa (AMG\_data \*mgl, AMG\_param \*param)
 Set up phase of smoothed aggregation AMG.

# 9.6.1 Detailed Description

Smoothed aggregation AMG: SETUP phase.

Note

Setup A, P, PT and levels using the unsmoothed aggregation algorithm; Refer to P. Vanek, J. Madel and M. Brezina "Algebraic Multigrid on Unstructured Meshes", 1994

Definition in file amg\_setup\_sa.c.

## 9.6.2 Function Documentation

```
9.6.2.1 SHORT fasp_amg_setup_sa ( AMG_data * mgl, AMG_param * param )
```

Set up phase of smoothed aggregation AMG.

70 File Documentation

#### **Parameters**

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

#### Returns

SUCCESS if succeed, error otherwise

**Author** 

Xiaozhe Hu

Date

09/29/2009

Note

Only for testing smoothed P and unsmoothed A, not used usually.

Modified by Chensong Zhang on 04/06/2010. Modified by Chensong Zhang on 05/09/2010. Modified by Xiaozhe Hu on 01/23/2011: add AMLI cycle Modified by Chensong Zhang on 05/10/2013: adjust the structure.

Definition at line 50 of file amg setup sa.c.

# 9.7 amg\_setup\_ua.c File Reference

Unsmoothed aggregation AMG: SETUP phase.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "amg_setup_aggregation_csr.inl"
#include "amg_setup_aggregation_bsr.inl"
```

#### **Functions**

- SHORT fasp amg setup ua (AMG data \*mgl, AMG param \*param)
  - Set up phase of unsmoothed aggregation AMG.
- SHORT fasp\_amg\_setup\_ua\_bsr (AMG\_data\_bsr \*mgl, AMG\_param \*param)

Set up phase of unsmoothed aggregation AMG (BSR format)

## 9.7.1 Detailed Description

Unsmoothed aggregation AMG: SETUP phase.

Note

Setup A, P, PT and levels using the unsmoothed aggregation algorithm; Refer to P. Vanek, J. Madel and M. Brezina "Algebraic Multigrid on Unstructured Meshes", 1994

Definition in file amg setup ua.c.

## 9.7.2 Function Documentation

```
9.7.2.1 SHORT fasp_amg_setup_ua ( AMG_data * mgl, AMG_param * param )
```

Set up phase of unsmoothed aggregation AMG.

## **Parameters**

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

## Returns

SUCCESS if succeed, error otherwise

**Author** 

Xiaozhe Hu

Date

12/28/2011

Definition at line 39 of file amg\_setup\_ua.c.

```
9.7.2.2 INT fasp_amg_setup_ua_bsr ( AMG_data_bsr * mgl, AMG_param * param )
```

Set up phase of unsmoothed aggregation AMG (BSR format)

## **Parameters**

mgl	Pointer to AMG data: AMG_data_bsr
param	Pointer to AMG parameters: AMG_param

#### Returns

SUCCESS if succeed, error otherwise

Author

Xiaozhe Hu

Date

03/16/2012

Definition at line 70 of file amg\_setup\_ua.c.

# 9.8 amg\_solve.c File Reference

Algebraic multigrid iterations: SOLVE phase.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

72 File Documentation

## **Functions**

```
    INT fasp_amg_solve (AMG_data *mgl, AMG_param *param)
```

AMG - SOLVE phase.

• INT fasp\_amg\_solve\_amli (AMG\_data \*mgl, AMG\_param \*param)

AMLI - SOLVE phase.

INT fasp\_amg\_solve\_nl\_amli (AMG\_data \*mgl, AMG\_param \*param)

Nonlinear AMLI — SOLVE phase.

void fasp\_famg\_solve (AMG\_data \*mgl, AMG\_param \*param)

FMG - SOLVE phase.

## 9.8.1 Detailed Description

Algebraic multigrid iterations: SOLVE phase.

Note

Solve Ax=b using multigrid method. This is SOLVE phase only and is independent of SETUP method used! Should be called after multigrid hierarchy has been generated!

Definition in file amg\_solve.c.

#### 9.8.2 Function Documentation

9.8.2.1 INT fasp\_amg\_solve ( AMG\_data \* mgl, AMG\_param \* param )

AMG - SOLVE phase.

#### **Parameters**

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

#### Returns

Iteration number if succeed, ERROR otherwise

Author

Xuehai Huang, Chensong Zhang

Date

04/02/2010

Modified by Chensong 04/21/2013: Fix an output typo

Definition at line 36 of file amg\_solve.c.

9.8.2.2 INT fasp\_amg\_solve\_amli ( AMG\_data \* mgl, AMG\_param \* param )

AMLI - SOLVE phase.

m	Pointer to AMG data: AMG_data	
para	Pointer to AMG parameters: AMG_param	

## Returns

Iteration number if succeed, ERROR otherwise

**Author** 

Xiaozhe Hu

Date

01/23/2011

Modified by Chensong 04/21/2013: Fix an output typo

Definition at line 119 of file amg\_solve.c.

9.8.2.3 INT fasp\_amg\_solve\_nl\_amli ( AMG\_data \* mgl, AMG\_param \* param )

Nonlinear AMLI — SOLVE phase.

## **Parameters**

	mgl	Pointer to AMG data: AMG_data
ĺ	param	Pointer to AMG parameters: AMG_param

### Returns

Iteration number if succeed, ERROR otherwise

Author

Xiaozhe Hu

Date

04/30/2011

Modified by Chensong 04/21/2013: Fix an output typo

Definition at line 198 of file amg\_solve.c.

9.8.2.4 void fasp\_famg\_solve (  $AMG\_data * mgl, AMG\_param * param$  )

FMG - SOLVE phase.

### **Parameters**

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

#### **Author**

Chensong Zhang

Date

01/10/2012

Definition at line 270 of file amg\_solve.c.

# 9.9 amlirecur.c File Reference

Abstract AMLI multilevel iteration - recursive version.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "forts_ns.h"
#include "mg_util.inl"
```

# **Functions**

- void fasp\_solver\_amli (AMG\_data \*mgl, AMG\_param \*param, INT level)

  Solve Ax=b with recursive AMLI-cycle.
- void fasp\_solver\_nl\_amli (AMG\_data \*mgl, AMG\_param \*param, INT level, INT num\_levels) Solve Ax=b with recursive nonlinear AMLI-cycle.
- void fasp\_solver\_nl\_amli\_bsr (AMG\_data\_bsr \*mgl, AMG\_param \*param, INT level, INT num\_levels)

  Solve Ax=b with recursive nonlinear AMLI-cycle.
- void fasp\_amg\_amli\_coef (const REAL lambda\_max, const REAL lambda\_min, const INT degree, REAL \*coef)
   Compute the coefficients of the polynomial used by AMLI-cycle.

# 9.9.1 Detailed Description

Abstract AMLI multilevel iteration – recursive version.

Note

Contains AMLI and nonlinear AMLI cycles

TODO: Need to add a non-recursive version! -Chensong

Definition in file amlirecur.c.

- 9.9.2 Function Documentation
- 9.9.2.1 void fasp\_amg\_amli\_coef ( const REAL lambda\_max, const REAL lambda\_min, const INT degree, REAL \* coef )

Compute the coefficients of the polynomial used by AMLI-cycle.

## **Parameters**

	lambda_max	Maximal lambda
	lambda_min	Minimal lambda
	degree	Degree of polynomial approximation
Ī	coef	Coefficient of AMLI (output)

**Author** 

Xiaozhe Hu

Date

01/23/2011

Definition at line 743 of file amlirecur.c.

9.9.2.2 void fasp\_solver\_amli ( AMG\_data \* mgl, AMG\_param \* param, INT level )

Solve Ax=b with recursive AMLI-cycle.

### **Parameters**

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param
level	Current level

# **Author**

Xiaozhe Hu

Date

01/23/2011

Modified by Chensong Zhang on 02/27/2013: update direct solvers.

Definition at line 37 of file amlirecur.c.

9.9.2.3 void fasp\_solver\_nl\_amli ( AMG\_data \* mgl, AMG\_param \* param, INT level, INT num\_levels )

Solve Ax=b with recursive nonlinear AMLI-cycle.

# **Parameters**

mgl	Pointer to AMG_data data
param	Pointer to AMG parameters
level	Current level
num_levels	Total numebr of levels

# Author

Xiaozhe Hu

Date

04/06/2010

Modified by Chensong Zhang on 02/27/2013: update direct solvers.

Definition at line 292 of file amlirecur.c.

```
9.9.2.4 void fasp_solver_nl_amli_bsr ( AMG_data_bsr * mgl, AMG_param * param, INT level, INT num_levels )
```

Solve Ax=b with recursive nonlinear AMLI-cycle.

#### **Parameters**

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param
level	Current level
num_levels	Total numebr of levels

### **Author**

Xiaozhe Hu

Date

04/06/2010

Modified by Chensong Zhang on 02/27/2013: update direct solvers.

Definition at line 565 of file amlirecur.c.

# 9.10 array.c File Reference

### Array operations.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

void fasp\_array\_null (REAL \*x)

Initialize an array.

void fasp\_array\_set (const INT n, REAL \*x, const REAL val)

Set initial value for an array to be x=val.

void fasp\_iarray\_set (const INT n, INT \*x, const INT val)

Set initial value for an array to be x=val.

void fasp\_array\_cp (const INT n, REAL \*x, REAL \*y)

Copy an array to the other y=x.

void fasp\_iarray\_cp (const INT n, INT \*x, INT \*y)

Copy an array to the other y=x.

```
• void fasp_array_cp_nc3 (REAL *x, REAL *y)
```

Copy an array to the other y=x, the length is 3.

void fasp\_array\_cp\_nc5 (REAL \*x, REAL \*y)

Copy an array to the other y=x, the length is 5.

void fasp\_array\_cp\_nc7 (REAL \*x, REAL \*y)

Copy an array to the other y=x, the length is 7.

# 9.10.1 Detailed Description

Array operations. Simple array operations - init, set, copy, etc

Definition in file array.c.

# 9.10.2 Function Documentation

```
9.10.2.1 void fasp_array_cp ( const INT n, REAL * x, REAL * y )
```

Copy an array to the other y=x.

### **Parameters**

n	Number of variables
X	Pointer to the original vector
У	Pointer to the destination vector

# Author

Chensong Zhang

Date

2010/04/03

Definition at line 172 of file array.c.

9.10.2.2 void fasp\_array\_cp\_nc3 ( REAL \* x, REAL \* y )

Copy an array to the other y=x, the length is 3.

### **Parameters**

X	Pointer to the original vector
у	Pointer to the destination vector

## **Author**

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Note

Special unrolled routine designed for a specific application

Definition at line 212 of file array.c.

```
9.10.2.3 void fasp_array_cp_nc5 ( REAL * x, REAL * y )
```

Copy an array to the other y=x, the length is 5.

#### **Parameters**

X	Pointer to the original vector
У	Pointer to the destination vector

### **Author**

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Note

Special unrolled routine designed for a specific application

Definition at line 233 of file array.c.

```
9.10.2.4 void fasp_array_cp_nc7 ( REAL * x, REAL * y )
```

Copy an array to the other y=x, the length is 7.

### **Parameters**

X	Pointer to the original vector
У	Pointer to the destination vector

# Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Note

Special unrolled routine designed for a specific application

Definition at line 256 of file array.c.

9.10.2.5 void fasp\_array\_null ( REAL \* x )

Initialize an array.

## **Parameters**

X	Pointer to the vector

**Author** 

Chensong Zhang

Date

2010/04/03

Definition at line 32 of file array.c.

9.10.2.6 void fasp\_array\_set ( const INT n, REAL \* x, const REAL val )

Set initial value for an array to be x=val.

## **Parameters**

n	Number of variables
X	Pointer to the vector
val	Initial value for the REAL array

#### **Author**

Chensong Zhang

Date

04/03/2010

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 52 of file array.c.

9.10.2.7 void fasp\_iarray\_cp ( const INT n, INT \* x, INT \* y )

Copy an array to the other y=x.

## **Parameters**

n	Number of variables
X	Pointer to the original vector
У	Pointer to the destination vector

# **Author**

Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 192 of file array.c.

```
9.10.2.8 void fasp_iarray_set ( const INT n, INT * x, const INT val )
```

Set initial value for an array to be x=val.

# **Parameters**

n	Number of variables
X	Pointer to the vector
val	Initial value for the REAL array

### **Author**

Chensong Zhang

Date

04/03/2010

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/25/2012

Definition at line 114 of file array.c.

# 9.11 blas\_array.c File Reference

BLAS operations for arrays.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

```
    void fasp_blas_array_ax (const INT n, const REAL a, REAL *x)
```

```
x = a * x
```

void fasp\_blas\_array\_axpy (const INT n, const REAL a, REAL \*x, REAL \*y)

```
y = a * x + y
```

void fasp\_blas\_array\_axpyz (const INT n, const REAL a, REAL \*x, REAL \*y, REAL \*z)

```
z = a * x + y
```

• void fasp\_blas\_array\_axpby (const INT n, const REAL a, REAL \*x, const REAL b, REAL \*y)

```
y = a*x + b*y
```

REAL fasp\_blas\_array\_dotprod (const INT n, REAL \*x, REAL \*y)
 Inner product of two arraies (x,y)

• REAL fasp\_blas\_array\_norm1 (const INT n, REAL \*x)

L1 norm of array x.

REAL fasp\_blas\_array\_norm2 (const INT n, REAL \*x)

L2 norm of array x.

• REAL fasp\_blas\_array\_norminf (const INT n, REAL \*x)

Linf norm of array x.

## 9.11.1 Detailed Description

BLAS operations for arrays.

Definition in file blas\_array.c.

### 9.11.2 Function Documentation

9.11.2.1 void fasp\_blas\_array\_ax ( const INT n, const REAL a, REAL \*x)

x = a \* x

## **Parameters**

n	Number of variables
а	Factor a
X	Pointer to x

### **Author**

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Note

x is reused to store the resulting array.

Definition at line 35 of file blas\_array.c.

9.11.2.2 void fasp\_blas\_array\_axpby ( const INT n, const REAL \* x, const REAL \* y )

y = a\*x + b\*y

n	Number of variables
а	Factor a
X	Pointer to x
b	Factor b
у	Pointer to y

**Author** 

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Note

y is reused to store the resulting array.

Definition at line 218 of file blas\_array.c.

9.11.2.3 void fasp\_blas\_array\_axpy ( const INT n, const REAL a, REAL \* x, REAL \* y )

y = a\*x + y

# **Parameters**

n	Number of variables
а	Factor a
X	Pointer to x
У	Pointer to y

### Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Note

y is reused to store the resulting array.

Definition at line 87 of file blas\_array.c.

9.11.2.4 void fasp\_blas\_array\_axpyz ( const INT n, const REAL a, REAL \* x, REAL \* y, REAL \* z )

z = a\*x + y

## **Parameters**

n	Number of variables
а	Factor a
X	Pointer to x
у	Pointer to y
Z	Pointer to z

# **Author**

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 167 of file blas\_array.c.

9.11.2.5 REAL fasp\_blas\_array\_dotprod ( const INT n, REAL \* x, REAL \* y )

Inner product of two arraies (x,y)

### **Parameters**

n	Number of variables
Х	Pointer to x
У	Pointer to y

## Returns

Inner product (x,y)

**Author** 

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 267 of file blas\_array.c.

9.11.2.6 REAL fasp\_blas\_array\_norm1 ( const INT n, REAL \* x )

L1 norm of array x.

n	Number of variables
X	Pointer to x

Returns

L1 norm of x

**Author** 

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 308 of file blas\_array.c.

9.11.2.7 REAL fasp\_blas\_array\_norm2 ( const INT n, REAL \* x )

L2 norm of array x.

### **Parameters**

n	Number of variables
X	Pointer to x

### Returns

L2 norm of x

**Author** 

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 348 of file blas\_array.c.

9.11.2.8 REAL fasp\_blas\_array\_norminf ( const INT n, REAL \* x )

Linf norm of array x.

### **Parameters**

n	Number of variables
X	Pointer to x

### Returns

L\_inf norm of x

### **Author**

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Zheng Li on 06/28/2012

Definition at line 388 of file blas\_array.c.

# 9.12 blas bcsr.c File Reference

BLAS operations for block\_dCSRmat matrices.

```
#include <time.h>
#include "fasp.h"
#include "fasp_block.h"
#include "fasp_functs.h"
```

### **Functions**

```
    void fasp_blas_bdcsr_aAxpy (const REAL alpha, block_dCSRmat *A, REAL *x, REAL *y)
```

Matrix-vector multiplication y = alpha\*A\*x + y.

void fasp blas bdcsr mxv (block dCSRmat \*A, REAL \*x, REAL \*y)

Matrix-vector multiplication y = A\*x.

void fasp\_blas\_bdbsr\_aAxpy (const REAL alpha, block\_BSR \*A, REAL \*x, REAL \*y)

Matrix-vector multiplication y = alpha\*A\*x + y.

void fasp\_blas\_bdbsr\_mxv (block\_BSR \*A, REAL \*x, REAL \*y)

Matrix-vector multiplication y = A\*x.

# 9.12.1 Detailed Description

BLAS operations for block\_dCSRmat matrices.

Definition in file blas bcsr.c.

# 9.12.2 Function Documentation

9.12.2.1 void fasp\_blas\_bdbsr\_aAxpy ( const REAL alpha, block\_BSR \* A, REAL \* x, REAL \* y )

Matrix-vector multiplication y = alpha\*A\*x + y.

## **Parameters**

alpha	REAL factor a
Α	Pointer to block_BSR matrix A
X	Pointer to array x
у	Pointer to array y

Author

Xiaozhe Hu

Date

11/11/2010

Definition at line 231 of file blas\_bcsr.c.

9.12.2.2 void fasp\_blas\_bdbsr\_mxv ( block\_BSR \* A, REAL \* x, REAL \* y )

Matrix-vector multiplication y = A\*x.

## **Parameters**

Α	Pointer to block_BSR matrix A
X	Pointer to array x
У	Pointer to array y

**Author** 

Xiaozhe Hu

Date

11/11/2010

Definition at line 269 of file blas\_bcsr.c.

9.12.2.3 void fasp\_blas\_bdcsr\_aAxpy ( const REAL alpha, block\_dCSRmat \* A, REAL \* X, REAL \* Y )

Matrix-vector multiplication y = alpha\*A\*x + y.

### **Parameters**

alpha	REAL factor a
Α	Pointer to block_dCSRmat matrix A
X	Pointer to array x
у	Pointer to array y

Author

Xiaozhe Hu

Date

06/04/2010

Definition at line 30 of file blas\_bcsr.c.

```
9.12.2.4 void fasp_blas_bdcsr_mxv ( block_dCSRmat * A, REAL * x, REAL * y )
```

Matrix-vector multiplication y = A\*x.

### **Parameters**

Α	Pointer to block_dCSRmat matrix A
X	Pointer to array x
у	Pointer to array y

### **Author**

Chensong Zhang

Date

04/27/2013

Definition at line 130 of file blas bcsr.c.

# 9.13 blas bsr.c File Reference

BLAS operations for dBSRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

- void fasp\_blas\_dbsr\_aAxpby (const REAL alpha, dBSRmat \*A, REAL \*x, const REAL beta, REAL \*y)
   Compute y := alpha\*A\*x + beta\*y.
- void fasp\_blas\_dbsr\_aAxpy (const REAL alpha, dBSRmat \*A, REAL \*x, REAL \*y)
   Compute y := alpha\*A\*x + y.
- void fasp\_blas\_dbsr\_mxv (dBSRmat \*A, REAL \*x, REAL \*y)

Compute y := A\*x.

void fasp\_blas\_dbsr\_rap1 (dBSRmat \*R, dBSRmat \*A, dBSRmat \*P, dBSRmat \*B)

dBSRmat sparse matrix multiplication B=R\*A\*P

void fasp\_blas\_dbsr\_rap (dBSRmat \*R, dBSRmat \*A, dBSRmat \*P, dBSRmat \*B)
 dBSRmat sparse matrix multiplication B=R\*A\*P

# 9.13.1 Detailed Description

BLAS operations for dBSRmat matrices.

Definition in file blas bsr.c.

# 9.13.2 Function Documentation

9.13.2.1 void fasp\_blas\_dbsr\_aAxpby ( const REAL alpha, dBSRmat \* A, REAL \* x, const REAL beta, REAL \* y)

Compute y := alpha\*A\*x + beta\*y.

alpha	REAL factor alpha
Α	Pointer to the dBSRmat matrix
X	Pointer to the array x
beta	REAL factor beta
у	Pointer to the array y

**Author** 

Zhiyang Zhou

Date

10/25/2010

Modified by Chunsheng Feng, Zheng Li

Date

06/29/2012

Note

Works for general nb (Xiaozhe)

Definition at line 39 of file blas\_bsr.c.

9.13.2.2 void fasp\_blas\_dbsr\_aAxpy ( const REAL alpha, dBSRmat \* A, REAL \* x, REAL \* y )

Compute y := alpha\*A\*x + y.

## **Parameters**

alpha	REAL factor alpha
Α	Pointer to the dBSRmat matrix
X	Pointer to the array x
У	Pointer to the array y

**Author** 

Zhiyang Zhou

Date

10/25/2010

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Note

Works for general nb (Xiaozhe)

Definition at line 320 of file blas\_bsr.c.

9.13.2.3 void fasp\_blas\_dbsr\_mxv ( dBSRmat \* A, REAL \* x, REAL \* y )

Compute y := A\*x.

Α	Pointer to the dBSRmat matrix
Χ	Pointer to the array x
у	Pointer to the array y

**Author** 

Zhiyang Zhou

Date

10/25/2010

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Note

Works for general nb (Xiaozhe)

Definition at line 595 of file blas\_bsr.c.

9.13.2.4 void fasp\_blas\_dbsr\_rap ( dBSRmat \* R, dBSRmat \* A, dBSRmat \* P, dBSRmat \* B)

dBSRmat sparse matrix multiplication B=R\*A\*P

### **Parameters**

R	Pointer to the dBSRmat matrix
Α	Pointer to the dBSRmat matrix
Р	Pointer to the dBSRmat matrix
В	Pointer to dBSRmat matrix equal to R*A*P (output)

# Author

Chunsheng Feng, Zheng Li

Date

10/24/2012

Note

Ref. R.E. Bank and C.C. Douglas. SMMP: Sparse Matrix Multiplication Package. Advances in Computational Mathematics, 1 (1993), pp. 127-137.

Definition at line 2528 of file blas\_bsr.c.

9.13.2.5 void fasp\_blas\_dbsr\_rap1 ( dBSRmat\*R, dBSRmat\*A, dBSRmat\*P, dBSRmat\*B)

dBSRmat sparse matrix multiplication B=R\*A\*P

#### **Parameters**

R	Pointer to the dBSRmat matrix
Α	Pointer to the dBSRmat matrix
Р	Pointer to the dBSRmat matrix
В	Pointer to dBSRmat matrix equal to R*A*P (output)

## Author

Chunsheng Feng, Xiaoqiang Yue and Xiaozhe Hu

Date

08/08/2011

Note

Ref. R.E. Bank and C.C. Douglas. SMMP: Sparse Matrix Multiplication Package. Advances in Computational Mathematics, 1 (1993), pp. 127-137.

Definition at line 2344 of file blas bsr.c.

# 9.14 blas csr.c File Reference

BLAS operations for dCSRmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

- INT fasp\_blas\_dcsr\_add (dCSRmat \*A, const REAL alpha, dCSRmat \*B, const REAL beta, dCSRmat \*C)
   compute C = alpha\*A + beta\*B in CSR format
- void fasp\_blas\_dcsr\_axm (dCSRmat \*A, const REAL alpha)

Multiply a sparse matrix A in CSR format by a scalar alpha.

void fasp\_blas\_dcsr\_mxv (dCSRmat \*A, REAL \*x, REAL \*y)

Matrix-vector multiplication y = A\*x.

void fasp\_blas\_dcsr\_mxv\_agg (dCSRmat \*A, REAL \*x, REAL \*y)

Matrix-vector multiplication y = A\*x, where the entries of A are all ones.

void fasp\_blas\_dcsr\_aAxpy (const REAL alpha, dCSRmat \*A, REAL \*x, REAL \*y)

Matrix-vector multiplication y = alpha\*A\*x + y.

void fasp\_blas\_dcsr\_aAxpy\_agg (const REAL alpha, dCSRmat \*A, REAL \*x, REAL \*y)

Matrix-vector multiplication y = alpha\*A\*x + y, where the entries of A are all ones.

REAL fasp\_blas\_dcsr\_vmv (dCSRmat \*A, REAL \*x, REAL \*y)

vector-Matrix-vector multiplication alpha = y'\*A\*x

void fasp blas dcsr mxm (dCSRmat \*A, dCSRmat \*B, dCSRmat \*C)

Sparse matrix multiplication C=A\*B.

• void fasp\_blas\_dcsr\_rap (dCSRmat \*R, dCSRmat \*A, dCSRmat \*P, dCSRmat \*RAP)

Triple sparse matrix multiplication B=R\*A\*P.

void fasp\_blas\_dcsr\_rap\_agg (dCSRmat \*R, dCSRmat \*A, dCSRmat \*P, dCSRmat \*RAP)

Triple sparse matrix multiplication B=R\*A\*P.

void fasp\_blas\_dcsr\_rap\_agg1 (dCSRmat \*R, dCSRmat \*A, dCSRmat \*P, dCSRmat \*B)

Triple sparse matrix multiplication B=R\*A\*P, where the entries of R and P are all ones.

void fasp\_blas\_dcsr\_ptap (dCSRmat \*Pt, dCSRmat \*A, dCSRmat \*P, dCSRmat \*Ac)

Triple sparse matrix multiplication B=P'\*A\*P.

void fasp blas dcsr rap4 (dCSRmat \*R, dCSRmat \*A, dCSRmat \*P, dCSRmat \*B, INT \*icor ysk)

Triple sparse matrix multiplication B=R\*A\*P.

## 9.14.1 Detailed Description

BLAS operations for dCSRmat matrices.

Note

Sparse functions usually contain three runs. The three runs are all the same but thy serve different purpose.

Example: If you do c=a+b:

- first do a dry run to find the number of non-zeroes in the result and form ic;
- allocate space (memory) for jc and form this one;
- if you only care about a "boolean" result of the addition, you stop here;
- you call another routine, which uses ic and jc to perform the addition.

Definition in file blas csr.c.

# 9.14.2 Function Documentation

9.14.2.1 void fasp\_blas\_dcsr\_aAxpy ( const REAL alpha, dCSRmat \* A, REAL \* x, REAL \* y )

Matrix-vector multiplication y = alpha\*A\*x + y.

### **Parameters**

alpha	REAL factor alpha
Α	Pointer to dCSRmat matrix A
Х	Pointer to array x
У	Pointer to array y

### **Author**

Chensong Zhang

Date

07/01/2009

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/26/2012

Definition at line 480 of file blas csr.c.

9.14.2.2 void fasp\_blas\_dcsr\_aAxpy\_agg ( const REAL alpha, dCSRmat \* A, REAL \* x, REAL \* y )

Matrix-vector multiplication y = alpha\*A\*x + y, where the entries of A are all ones.

#### **Parameters**

alpha	REAL factor alpha
Α	Pointer to dCSRmat matrix A
X	Pointer to array x
у	Pointer to array y

**Author** 

Xiaozhe Hu

Date

02/22/2011

Modified by Chunsheng Feng, Zheng Li on 08/29/2012

Definition at line 594 of file blas\_csr.c.

9.14.2.3 void fasp\_blas\_dcsr\_add ( dCSRmat \* A, const REAL alpha, dCSRmat \* B, const REAL beta, dCSRmat \* C)

compute C = alpha\*A + beta\*B in CSR format

### **Parameters**

Α	Pointer to dCSRmat matrix
alpha	REAL factor alpha
В	Pointer to dCSRmat matrix
beta	REAL factor beta
С	Pointer to dCSRmat matrix

# Returns

SUCCESS if succees, RUN\_FAIL if not

Author

Xiaozhe Hu

Date

11/07/2009

Modified by Chunsheng Feng, Zheng Li on 06/29/2012

Definition at line 48 of file blas\_csr.c.

9.14.2.4 void fasp\_blas\_dcsr\_axm ( dCSRmat \* A, const REAL alpha )

Multiply a sparse matrix A in CSR format by a scalar alpha.

	Α	Pointer to dCSRmat matrix A
alp	ha	REAL factor alpha

# **Author**

Chensong Zhang

Date

07/01/2009

Modified by Chunsheng Feng, Zheng Li on 06/29/2012

Definition at line 201 of file blas\_csr.c.

9.14.2.5 void fasp\_blas\_dcsr\_mxm ( dCSRmat \* A, dCSRmat \* B, dCSRmat \* C)

Sparse matrix multiplication C=A\*B.

## **Parameters**

Α	Pointer to the dCSRmat matrix A
В	Pointer to the dCSRmat matrix B
С	Pointer to dCSRmat matrix equal to A*B

## Author

Xiaozhe Hu

Date

11/07/2009

Note

This fct will be replaced! -Chensong

Definition at line 760 of file blas\_csr.c.

9.14.2.6 void fasp\_blas\_dcsr\_mxv ( dCSRmat \* A, REAL \* x, REAL \* y )

Matrix-vector multiplication y = A\*x.

## **Parameters**

Α	Pointer to dCSRmat matrix A
X	Pointer to array x

У	Pointer to array y
,	, ,

Author

Chensong Zhang

Date

07/01/2009

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/26/2012

Definition at line 225 of file blas\_csr.c.

9.14.2.7 void fasp\_blas\_dcsr\_mxv\_agg ( dCSRmat \* A, REAL \* X, REAL \* Y )

Matrix-vector multiplication y = A\*x, where the entries of A are all ones.

## **Parameters**

Α	Pointer to dCSRmat matrix A
X	Pointer to array x
у	Pointer to array y

**Author** 

Xiaozhe Hu

Date

02/22/2011

Modified by Chunsheng Feng, Zheng Li on 08/29/2012

Definition at line 423 of file blas\_csr.c.

9.14.2.8 void fasp\_blas\_dcsr\_ptap ( dCSRmat \* Pt, dCSRmat \* A, dCSRmat \* P, dCSRmat \* Ac )

Triple sparse matrix multiplication B=P'\*A\*P.

### **Parameters**

Pt	Pointer to the restriction matrix
Α	Pointer to the fine coefficient matrix
Р	Pointer to the prolongation matrix
Ac	Pointer to the coarse coefficient matrix (output)

### **Author**

Ludmil Zikatanov, Chensong Zhang

Date

05/10/2010

Modified by Chunsheng Feng, Zheng Li on 10/19/2012

Note

Driver to compute triple matrix product P'\*A\*P using Itz CSR format. In Itx format: ia[0]=1, ja[0] and a[0] are used as usual. When called from Fortran, ia[0], ja[0] and a[0] will be just ia(1),ja(1),a(1). For the indices,  $ia_t[tz[k] = a_usual[k]+1$ ,  $ja_t[tz[k] = a_usual[k]+1]$ 

Definition at line 1598 of file blas\_csr.c.

9.14.2.9 void fasp\_blas\_dcsr\_rap ( dCSRmat \* R, dCSRmat \* A, dCSRmat \* P, dCSRmat \* RAP )

Triple sparse matrix multiplication B=R\*A\*P.

#### **Parameters**

R	Pointer to the dCSRmat matrix R
Α	Pointer to the dCSRmat matrix A
Р	Pointer to the dCSRmat matrix P
RAP	Pointer to dCSRmat matrix equal to R*A*P

### **Author**

Xuehai Huang, Chensong Zhang

Date

05/10/2010

Modified by Chunsheng Feng, Xiaogiang Yue on 05/26/2012

Note

Ref. R.E. Bank and C.C. Douglas. SMMP: Sparse Matrix Multiplication Package. Advances in Computational Mathematics, 1 (1993), pp. 127-137.

Definition at line 867 of file blas csr.c.

9.14.2.10 void fasp\_blas\_dcsr\_rap4 ( dCSRmat \* R, dCSRmat \* A, dCSRmat \* P, dCSRmat \* B, INT \* icor\_ysk )

Triple sparse matrix multiplication B=R\*A\*P.

### **Parameters**

R	pointer to the dCSRmat matrix
Α	pointer to the dCSRmat matrix

Р	pointer to the dCSRmat matrix
В	pointer to dCSRmat matrix equal to R*A*P
icor_ysk	pointer to the array

#### **Author**

Feng Chunsheng, Yue Xiaoqiang

Date

08/02/2011

Note

Ref. R.E. Bank and C.C. Douglas. SMMP: Sparse Matrix Multiplication Package. Advances in Computational Mathematics, 1 (1993), pp. 127-137.

Definition at line 1697 of file blas\_csr.c.

9.14.2.11 void fasp\_blas\_dcsr\_rap\_agg ( dCSRmat \* R, dCSRmat \* A, dCSRmat \* P, dCSRmat \* RAP )

Triple sparse matrix multiplication B=R\*A\*P.

#### **Parameters**

R	Pointer to the dCSRmat matrix R
Α	Pointer to the dCSRmat matrix A
Р	Pointer to the dCSRmat matrix P
RAP	Pointer to dCSRmat matrix equal to R*A*P

## **Author**

Xuehai Huang, Chensong Zhang

Date

05/10/2010

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/26/2012

Note

Ref. R.E. Bank and C.C. Douglas. SMMP: Sparse Matrix Multiplication Package. Advances in Computational Mathematics, 1 (1993), pp. 127-137.

Definition at line 1148 of file blas\_csr.c.

9.14.2.12 void fasp\_blas\_dcsr\_rap\_agg1 ( dCSRmat \* R, dCSRmat \* A, dCSRmat \* P, dCSRmat \* B)

Triple sparse matrix multiplication B=R\*A\*P, where the entries of R and P are all ones.

R	Pointer to the dCSRmat matrix R
Α	Pointer to the dCSRmat matrix A
Р	Pointer to the dCSRmat matrix P
В	Pointer to dCSRmat matrix equal to R*A*P

## **Author**

Xiaozhe Hu

Date

02/21/2011

Note

Ref. R.E. Bank and C.C. Douglas. SMMP: Sparse Matrix Multiplication Package. Advances in Computational Mathematics, 1 (1993), pp. 127-137.

Definition at line 1415 of file blas\_csr.c.

```
9.14.2.13 REAL fasp_blas_dcsr_vmv ( dCSRmat * A, REAL * x, REAL * y )
```

vector-Matrix-vector multiplication alpha = y'\*A\*x

### **Parameters**

Α	Pointer to dCSRmat matrix A
X	Pointer to array x
У	Pointer to array y

# Author

Chensong Zhang

Date

07/01/2009

Definition at line 705 of file blas\_csr.c.

# 9.15 blas\_csrl.c File Reference

BLAS operations for dCSRLmat matrices.

```
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

void fasp\_blas\_dcsrl\_mxv (dCSRLmat \*A, REAL \*x, REAL \*y)
 Compute y = A\*x for a sparse matrix in CSRL format.

# 9.15.1 Detailed Description

BLAS operations for dCSRLmat matrices.

Note

For details of CSRL format, refer to "Optimizaing sparse matrix vector product computations using unroll and jam" by John Mellor-Crummey and John Garvin, Tech Report Rice Univ, Aug 2002.

Definition in file blas csrl.c.

## 9.15.2 Function Documentation

```
9.15.2.1 void fasp_blas_dcsrl_mxv ( dCSRLmat * A, REAL * x, REAL * y )
```

Compute y = A\*x for a sparse matrix in CSRL format.

### **Parameters**

Α	Pointer to dCSRLmat matrix A
X	Pointer to REAL array of vector x
У	Pointer to REAL array of vector y

Date

2011/01/07

Definition at line 28 of file blas csrl.c.

# 9.16 blas smat.c File Reference

BLAS operations for small full matrix.

```
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

- void fasp\_blas\_smat\_mxv\_nc2 (REAL \*a, REAL \*b, REAL \*c)
  - Compute the product of a 2\*2 matrix a and a array b, stored in c.
- void fasp\_blas\_smat\_mxv\_nc3 (REAL \*a, REAL \*b, REAL \*c)
  - Compute the product of a 3\*3 matrix a and a array b, stored in c.
- void fasp\_blas\_smat\_mxv\_nc5 (REAL \*a, REAL \*b, REAL \*c)
  - Compute the product of a 5\*5 matrix a and a array b, stored in c.
- void fasp\_blas\_smat\_mxv\_nc7 (REAL \*a, REAL \*b, REAL \*c)
  - Compute the product of a 7\*7 matrix a and a array b, stored in c.
- void fasp\_blas\_smat\_mxv (REAL \*a, REAL \*b, REAL \*c, const INT n)
  - Compute the product of a small full matrix a and a array b, stored in c.
- void fasp blas smat mul nc2 (REAL \*a, REAL \*b, REAL \*c)

```
Compute the matrix product of two 2* matrices a and b, stored in c.

    void fasp_blas_smat_mul_nc3 (REAL *a, REAL *b, REAL *c)

      Compute the matrix product of two 3*3 matrices a and b, stored in c.

    void fasp blas smat mul nc5 (REAL *a, REAL *b, REAL *c)

      Compute the matrix product of two 5*5 matrices a and b, stored in c.

    void fasp_blas_smat_mul_nc7 (REAL *a, REAL *b, REAL *c)

      Compute the matrix product of two 7*7 matrices a and b, stored in c.

    void fasp blas smat mul (REAL *a, REAL *b, REAL *c, const INT n)

      Compute the matrix product of two small full matrices a and b, stored in c.

    void fasp_blas_array_axpyz_nc2 (REAL a, REAL *x, REAL *y, REAL *z)

      z = a * x + v

    void fasp_blas_array_axpyz_nc3 (const REAL a, REAL *x, REAL *y, REAL *z)

      z = a * x + y

    void fasp_blas_array_axpyz_nc5 (const REAL a, REAL *x, REAL *y, REAL *z)

      z = a * x + v

    void fasp_blas_array_axpyz_nc7 (const REAL a, REAL *x, REAL *y, REAL *z)

      z = a * x + y

    void fasp_blas_array_axpy_nc2 (const REAL a, REAL *x, REAL *y)

      y = a * x + y, the length of x and y is 2

    void fasp_blas_array_axpy_nc3 (const REAL a, REAL *x, REAL *y)

      y = a*x + y, the length of x and y is 3

    void fasp_blas_array_axpy_nc5 (const REAL a, REAL *x, REAL *y)

      y = a*x + y, the length of x and y is 5

    void fasp_blas_array_axpy_nc7 (const REAL a, REAL *x, REAL *y)

      y = a*x + y, the length of x and y is 7

    void fasp_blas_smat_ypAx_nc2 (REAL *A, REAL *x, REAL *y)

      Compute y := y + Ax, where 'A' is a 2*2 dense matrix.

    void fasp_blas_smat_ypAx_nc3 (REAL *A, REAL *x, REAL *y)

      Compute y := y + Ax, where 'A' is a 3*3 dense matrix.

    void fasp_blas_smat_ypAx_nc5 (REAL *A, REAL *x, REAL *y)

      Compute y := y + Ax, where 'A' is a 5*5 dense matrix.

    void fasp_blas_smat_ypAx_nc7 (REAL *A, REAL *x, REAL *y)

      Compute y := y + Ax, where 'A' is a 7*7 dense matrix.

    void fasp blas smat ypAx (REAL *A, REAL *x, REAL *y, const INT n)

      Compute y := y + Ax, where 'A' is a n*n dense matrix.

    void fasp blas smat ymAx nc2 (REAL *A, REAL *x, REAL *y)

      Compute y := y - Ax, where 'A' is a n*n dense matrix.

    void fasp blas smat ymAx nc3 (REAL *A, REAL *x, REAL *y)

      Compute y := y - Ax, where 'A' is a n*n dense matrix.

    void fasp_blas_smat_ymAx_nc5 (REAL *A, REAL *x, REAL *y)

      Compute y := y - Ax, where 'A' is a n*n dense matrix.

    void fasp blas smat ymAx nc7 (REAL *A, REAL *x, REAL *y)

      Compute y := y - Ax, where 'A' is a 7*7 dense matrix.

    void fasp_blas_smat_ymAx (REAL *A, REAL *x, REAL *y, INT n)

      Compute y := y - Ax, where 'A' is a n*n dense matrix.

    void fasp blas smat aAxpby (const REAL alpha, REAL *A, REAL *x, const REAL beta, REAL *y, const INT n)

      Compute y:=alpha*A*x + beta*y.
```

void fasp\_blas\_smat\_ymAx\_ns2 (REAL \*A, REAL \*x, REAL \*y)

Compute ys := ys - Ass\*xs, where 'A' is a 2\*2 dense matrix, Ass is its saturaton part 1\*1.

void fasp\_blas\_smat\_ymAx\_ns3 (REAL \*A, REAL \*x, REAL \*y)

Compute ys := ys - Ass\*xs, where 'A' is a 3\*3 dense matrix, Ass is its saturaton part 2\*2.

void fasp\_blas\_smat\_ymAx\_ns5 (REAL \*A, REAL \*x, REAL \*y)

Compute ys := ys - Ass\*xs, where 'A' is a 5\*5 dense matrix, Ass is its saturaton part 4\*4.

void fasp\_blas\_smat\_ymAx\_ns7 (REAL \*A, REAL \*x, REAL \*y)

Compute ys := ys - Ass\*xs, where 'A' is a 7\*7 dense matrix, Ass is its saturaton part 6\*6.

void fasp blas smat ymAx ns (REAL \*A, REAL \*x, REAL \*y, const INT n)

Compute ys := ys - Ass\*xs, where 'A' is a n\*n dense matrix, Ass is its saturaton part (n-1)\*(n-1).

## 9.16.1 Detailed Description

BLAS operations for small full matrix.

Definition in file blas smat.c.

## 9.16.2 Function Documentation

9.16.2.1 void fasp\_blas\_array\_axpy\_nc2 ( const REAL a, REAL \* x, REAL \* y )

y = a\*x + y, the length of x and y is 2

#### **Parameters**

а	REAL factor a
Х	Pointer to the original array
у	Pointer to the destination array

## **Author**

Xiaozhe Hu

Date

18/11/2011

Definition at line 627 of file blas smat.c.

9.16.2.2 void fasp\_blas\_array\_axpy\_nc3 ( const REAL a, REAL \* x, REAL \* y )

y = a\*x + y, the length of x and y is 3

### **Parameters**

	а	REAL factor a
ſ	Х	Pointer to the original array

V	Pointer to the destination array
,	Tomtor to the decimation and

**Author** 

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 650 of file blas\_smat.c.

9.16.2.3 void fasp\_blas\_array\_axpy\_nc5 ( const REAL a, REAL \* x, REAL \* y )

y = a\*x + y, the length of x and y is 5

### **Parameters**

а	REAL factor a
X	Pointer to the original array
у	Pointer to the destination array

### **Author**

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 679 of file blas\_smat.c.

9.16.2.4 void fasp\_blas\_array\_axpy\_nc7 ( const REAL a, REAL \* x, REAL \* y )

y = a\*x + y, the length of x and y is 7

# **Parameters**

а	REAL factor a
Χ	Pointer to the original array
у	Pointer to the destination array

## **Author**

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 726 of file blas\_smat.c.

9.16.2.5 void fasp\_blas\_array\_axpyz\_nc2 ( REAL \* x, REAL \* y, REAL \* z )

z = a\*x + y

## **Parameters**

а	REAL factor a
X	Pointer to the original array 1
У	Pointer to the original array 2
Z	Pointer to the destination array

### **Author**

Xiaozhe Hu

Date

18/11/2011

Note

z is the third array and the length of x, y and z is 2

Definition at line 442 of file blas\_smat.c.

9.16.2.6 void fasp\_blas\_array\_axpyz\_nc3 ( const REAL a, REAL \* x, REAL \* y, REAL \* z )

z = a\*x + y

## **Parameters**

а	REAL factor a
X	Pointer to the original array 1
У	Pointer to the original array 2
Z	Pointer to the destination array

# **Author**

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Note

z is the third array and the length of  $x,\,y$  and z is 3

Definition at line 469 of file blas\_smat.c.

9.16.2.7 void fasp\_blas\_array\_axpyz\_nc5 ( const REAL a, REAL \* x, REAL \* y, REAL \* z )

z = a\*x + y

а	REAL factor a
X	Pointer to the original array 1
у	Pointer to the original array 2
Z	Pointer to the destination array

### **Author**

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Note

z is the third array and the length of x, y and z is 5

Definition at line 502 of file blas\_smat.c.

9.16.2.8 void fasp\_blas\_array\_axpyz\_nc7 ( const REAL a, REAL \* x, REAL \* y, REAL \* z )

z = a\*x + y

### **Parameters**

а	REAL factor a
X	Pointer to the original array 1
У	Pointer to the original array 2
Z	Pointer to the destination array

### Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Note

z is the third array and the length of x, y and z is 7

Definition at line 553 of file blas\_smat.c.

9.16.2.9 void fasp\_blas\_smat\_aAxpby ( const REAL alpha, REAL \* A, REAL \* x, const REAL beta, REAL \* y, const INT n)

Compute y:=alpha\*A\*x + beta\*y.

## **Parameters**

alpha	REAL factor alpha
Α	Pointer to the REAL array which stands for a n∗n full matrix
X	Pointer to the REAL array with length n
beta	REAL factor beta
у	Pointer to the REAL array with length n
n	Length of array x and y

## **Author**

Zhiyang Zhou

Date

2010/10/25

Definition at line 1250 of file blas\_smat.c.

9.16.2.10 void fasp\_blas\_smat\_mul ( REAL \* a, REAL \* b, REAL \* c, const INT n )

Compute the matrix product of two small full matrices a and b, stored in c.

# **Parameters**

а	Pointer to the REAL array which stands a n∗n matrix
b	Pointer to the REAL array which stands a n∗n matrix
С	Pointer to the REAL array which stands a n∗n matrix
n	Dimension of the matrix

# Author

Xiaozhe Hu, Shiquan Zhang

Date

04/21/2010

Definition at line 390 of file blas\_smat.c.

9.16.2.11 void fasp\_blas\_smat\_mul\_nc2 ( REAL \* a, REAL \* b, REAL \* c )

Compute the matrix product of two 2\* matrices a and b, stored in c.

# **Parameters**

а	Pointer to the REAL array which stands a n∗n matrix
b	Pointer to the REAL array which stands a n∗n matrix
С	Pointer to the REAL array which stands a n∗n matrix

## **Author**

Xiaozhe Hu

Date

18/11/2011

Definition at line 175 of file blas\_smat.c.

9.16.2.12 void fasp\_blas\_smat\_mul\_nc3 ( REAL \* a, REAL \* b, REAL \* c )

Compute the matrix product of two 3\*3 matrices a and b, stored in c.

#### **Parameters**

а	Pointer to the REAL array which stands a n*n matrix
b	Pointer to the REAL array which stands a n*n matrix
С	Pointer to the REAL array which stands a n*n matrix

## **Author**

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 204 of file blas\_smat.c.

9.16.2.13 void fasp\_blas\_smat\_mul\_nc5 ( REAL \* a, REAL \* b, REAL \* c )

Compute the matrix product of two 5\*5 matrices a and b, stored in c.

# **Parameters**

а	Pointer to the REAL array which stands a 5∗5 matrix
b	Pointer to the REAL array which stands a 5∗5 matrix
С	Pointer to the REAL array which stands a 5*5 matrix

## **Author**

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 241 of file blas\_smat.c.

9.16.2.14 void fasp\_blas\_smat\_mul\_nc7 ( REAL \* a, REAL \* b, REAL \* c )

Compute the matrix product of two 7\*7 matrices a and b, stored in c.

## **Parameters**

а	Pointer to the REAL array which stands a 7*7 matrix
b	Pointer to the REAL array which stands a 7*7 matrix
С	Pointer to the REAL array which stands a 7*7 matrix

## **Author**

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 300 of file blas smat.c.

9.16.2.15 void fasp\_blas\_smat\_mxv ( REAL \* a, REAL \* b, REAL \* c, const INT n )

Compute the product of a small full matrix a and a array b, stored in c.

#### **Parameters**

а	Pointer to the REAL array which stands a n∗n matrix
b	Pointer to the REAL array with length n
С	Pointer to the REAL array with length n
n	Dimension of the matrix

## **Author**

Xiaozhe Hu, Shiquan Zhang

Date

04/21/2010

Definition at line 125 of file blas\_smat.c.

9.16.2.16 void fasp\_blas\_smat\_mxv\_nc2 ( REAL \* a, REAL \* b, REAL \* c )

Compute the product of a 2\*2 matrix a and a array b, stored in c.

## **Parameters**

а	Pointer to the REAL array which stands a 2*2 matrix
b	Pointer to the REAL array with length 2
С	Pointer to the REAL array with length 2

## **Author**

Xiaozhe Hu

Date

18/11/2010

Definition at line 25 of file blas\_smat.c.

9.16.2.17 void fasp\_blas\_smat\_mxv\_nc3 ( REAL \* a, REAL \* b, REAL \* c )

Compute the product of a 3\*3 matrix a and a array b, stored in c.

## **Parameters**

а	Pointer to the REAL array which stands a 3*3 matrix
b	Pointer to the REAL array with length 3
С	Pointer to the REAL array with length 3

## **Author**

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 47 of file blas\_smat.c.

9.16.2.18 void fasp\_blas\_smat\_mxv\_nc5 ( REAL \* a, REAL \* b, REAL \* c )

Compute the product of a 5\*5 matrix a and a array b, stored in c.

## **Parameters**

а	Pointer to the REAL array which stands a 5*5 matrix
b	Pointer to the REAL array with length 5
С	Pointer to the REAL array with length 5

#### **Author**

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 70 of file blas\_smat.c.

9.16.2.19 void fasp\_blas\_smat\_mxv\_nc7 ( REAL \* a, REAL \* b, REAL \* c )

Compute the product of a 7\*7 matrix a and a array b, stored in c.

## **Parameters**

а	Pointer to the REAL array which stands a 7*7 matrix
b	Pointer to the REAL array with length 7
С	Pointer to the REAL array with length 7

## **Author**

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 96 of file blas\_smat.c.

9.16.2.20 void fasp\_blas\_smat\_ymAx ( REAL \* A, REAL \* X, REAL \* Y, INT n )

Compute y := y - Ax, where 'A' is a n\*n dense matrix.

## **Parameters**

Α	Pointer to the n∗n dense matrix
X	Pointer to the REAL array with length n
у	Pointer to the REAL array with length n
n	the dimension of the dense matrix

#### **Author**

Zhiyang Zhou, Xiaozhe Hu

Date

2010/10/25

Definition at line 1149 of file blas\_smat.c.

9.16.2.21 void fasp\_blas\_smat\_ymAx\_nc2 ( REAL \* A, REAL \* X, REAL \* Y )

Compute y := y - Ax, where 'A' is a n\*n dense matrix.

## **Parameters**

Α	Pointer to the 2*2 dense matrix
Χ	Pointer to the REAL array with length 3
У	Pointer to the REAL array with length 3

## **Author**

Xiaozhe Hu

Date

18/11/2011

Note

Works for 2-component

Definition at line 1019 of file blas\_smat.c.

9.16.2.22 void fasp\_blas\_smat\_ymAx\_nc3 ( REAL \* A, REAL \* X, REAL \* Y )

Compute y := y - Ax, where 'A' is a n\*n dense matrix.

## **Parameters**

Α	Pointer to the 3*3 dense matrix
Χ	Pointer to the REAL array with length 3

y Pointer to the REAL array with length 3

**Author** 

Xiaozhe Hu, Zhiyang Zhou

Date

01/06/2011

Note

Works for 3-component

Definition at line 1047 of file blas\_smat.c.

9.16.2.23 void fasp\_blas\_smat\_ymAx\_nc5 ( REAL \* A, REAL \* X, REAL \* Y )

Compute y := y - Ax, where 'A' is a n\*n dense matrix.

## **Parameters**

Α	Pointer to the 5*5 dense matrix
X	Pointer to the REAL array with length 5
У	Pointer to the REAL array with length 5

#### Author

Xiaozhe Hu, Zhiyang Zhou

Date

01/06/2011

Note

Works for 5-component

Definition at line 1077 of file blas\_smat.c.

9.16.2.24 void fasp\_blas\_smat\_ymAx\_nc7 ( REAL \* A, REAL \* X, REAL \* Y )

Compute y := y - Ax, where 'A' is a 7\*7 dense matrix.

## **Parameters**

Α	Pointer to the 7*7 dense matrix
Х	Pointer to the REAL array with length 7

y Pointer to the REAL array with length 7

**Author** 

Xiaozhe Hu, Zhiyang Zhou

Date

01/06/2011

Note

Works for 7-component

Definition at line 1111 of file blas\_smat.c.

9.16.2.25 void fasp\_blas\_smat\_ymAx\_ns ( REAL \* A, REAL \* X, REAL \* Y, const INT X)

Compute ys := ys - Ass\*xs, where 'A' is a n\*n dense matrix, Ass is its saturaton part (n-1)\*(n-1).

## **Parameters**

Α	Pointer to the n*n dense matrix
Х	Pointer to the REAL array with length n-1
у	Pointer to the REAL array with length n-1
n	the dimension of the dense matrix

Author

Xiaozhe Hu

Date

2010/10/25

Note

Only for block smoother for saturation block without explictly use saturation block!!

Definition at line 1424 of file blas\_smat.c.

9.16.2.26 void fasp\_blas\_smat\_ymAx\_ns2 ( REAL \* A, REAL \* X, REAL \* Y )

Compute ys := ys - Ass\*xs, where 'A' is a 2\*2 dense matrix, Ass is its saturaton part 1\*1.

**Parameters** 

A Pointer to the 2\*2 dense matrix

X	Pointer to the REAL array with length 1
у	Pointer to the REAL array with length 1

## **Author**

Xiaozhe Hu

Date

2011/11/18

#### Note

Works for 2-component (Xiaozhe) Only for block smoother for saturation block without explicitly use saturation block!!

Definition at line 1300 of file blas\_smat.c.

9.16.2.27 void fasp\_blas\_smat\_ymAx\_ns3 ( REAL \* A, REAL \* X, REAL \* Y )

Compute ys := ys - Ass\*xs, where 'A' is a 3\*3 dense matrix, Ass is its saturation part 2\*2.

#### **Parameters**

Α	Pointer to the 3*3 dense matrix
Х	Pointer to the REAL array with length 2
у	Pointer to the REAL array with length 2

#### **Author**

Xiaozhe Hu

Date

2010/10/25

#### Note

Works for 3-component (Xiaozhe) Only for block smoother for saturation block without explictly use saturation block!!

Definition at line 1324 of file blas smat.c.

9.16.2.28 void fasp\_blas\_smat\_ymAx\_ns5 ( REAL \* A, REAL \* X, REAL \* Y )

Compute ys := ys - Ass\*xs, where 'A' is a 5\*5 dense matrix, Ass is its saturaton part 4\*4.

**Parameters** 

Α	Pointer to the 5*5 dense matrix
X	Pointer to the REAL array with length 4
у	Pointer to the REAL array with length 4

#### Author

Xiaozhe Hu

Date

2010/10/25

Note

Works for 5-component (Xiaozhe) Only for block smoother for saturation block without explictly use saturation block!!

Definition at line 1352 of file blas\_smat.c.

9.16.2.29 void fasp\_blas\_smat\_ymAx\_ns7 ( REAL \* A, REAL \* X, REAL \* Y )

Compute ys := ys - Ass\*xs, where 'A' is a 7\*7 dense matrix, Ass is its saturaton part 6\*6.

## **Parameters**

Α	Pointer to the 7*7 dense matrix
X	Pointer to the REAL array with length 6
у	Pointer to the REAL array with length 6

#### Author

Xiaozhe Hu

Date

2010/10/25

Note

Works for 7-component (Xiaozhe) Only for block smoother for saturation block without explicitly use saturation block!!

Definition at line 1386 of file blas\_smat.c.

9.16.2.30 void fasp\_blas\_smat\_ypAx ( REAL \* A, REAL \* X, REAL \* Y, const INT n )

Compute y := y + Ax, where 'A' is a n\*n dense matrix.

## **Parameters**

Α	Pointer to the n*n dense matrix
X	Pointer to the REAL array with length n
у	Pointer to the REAL array with length n
n	Dimension of the dense matrix

## **Author**

Zhiyang Zhou

Date

2010/10/25

Definition at line 918 of file blas\_smat.c.

9.16.2.31 void fasp\_blas\_smat\_ypAx\_nc2 ( REAL \* A, REAL \* X, REAL \* Y )

Compute y := y + Ax, where 'A' is a 2\*2 dense matrix.

## **Parameters**

Α	Pointer to the 3*3 dense matrix
X	Pointer to the REAL array with length 3
У	Pointer to the REAL array with length 3

## **Author**

Xiaozhe Hu

Date

2011/11/18

Definition at line 799 of file blas\_smat.c.

9.16.2.32 void fasp\_blas\_smat\_ypAx\_nc3 ( REAL \* A, REAL \* X, REAL \* Y )

Compute y := y + Ax, where 'A' is a 3\*3 dense matrix.

## **Parameters**

Α	Pointer to the 3*3 dense matrix
X	Pointer to the REAL array with length 3
У	Pointer to the REAL array with length 3

#### **Author**

Zhiyang Zhou, Xiaozhe Hu

Date

2010/10/25

Definition at line 825 of file blas\_smat.c.

9.16.2.33 void fasp\_blas\_smat\_ypAx\_nc5 ( REAL \* A, REAL \* X, REAL \* Y )

Compute y := y + Ax, where 'A' is a 5\*5 dense matrix.

## **Parameters**

Α	Pointer to the 5*5 dense matrix
X	Pointer to the REAL array with length 5
у	Pointer to the REAL array with length 5

#### **Author**

Zhiyang Zhou, Xiaozhe Hu

Date

2010/10/25

Definition at line 852 of file blas\_smat.c.

```
9.16.2.34 void fasp_blas_smat_ypAx_nc7 ( REAL * A, REAL * X, REAL * Y )
```

Compute y := y + Ax, where 'A' is a 7\*7 dense matrix.

#### **Parameters**

Α	Pointer to the 7*7 dense matrix
X	Pointer to the REAL array with length 7
У	Pointer to the REAL array with length 7

### **Author**

Zhiyang Zhou, Xiaozhe Hu

Date

2010/10/25

Definition at line 883 of file blas\_smat.c.

# 9.17 blas\_str.c File Reference

BLAS operations for dSTRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

```
\bullet \ \ void \ fasp\_blas\_dstr\_aAxpy \ (REAL \ alpha, \ dSTRmat \ *A, \ REAL \ *x, \ REAL \ *y)\\
```

Matrix-vector multiplication y = alpha\*A\*x + y.
• void fasp\_blas\_dstr\_mxv (dSTRmat \*A, REAL \*x, REAL \*y)

Matrix-vector multiplication y = A\*x.

INT fasp\_dstr\_diagscale (dSTRmat \*A, dSTRmat \*B)
 B=D^{-1}A.

# 9.17.1 Detailed Description

BLAS operations for dSTRmat matrices.

Definition in file blas\_str.c.

# 9.17.2 Function Documentation

9.17.2.1 void fasp\_blas\_dstr\_aAxpy ( REAL alpha, dSTRmat \* A, REAL \* x, REAL \* y )

Matrix-vector multiplication y = alpha\*A\*x + y.

## **Parameters**

alpha	REAL factor alpha
Α	Pointer to dSTRmat matrix
X	Pointer to REAL array
У	Pointer to REAL array

## **Author**

Zhiyang Zhou, Xiaozhe Hu, Shiquan Zhang

Date

2010/10/15

Definition at line 47 of file blas\_str.c.

9.17.2.2 void fasp\_blas\_dstr\_mxv ( dSTRmat \* A, REAL \* x, REAL \* y)

Matrix-vector multiplication y = A\*x.

## **Parameters**

Α	Pointer to dSTRmat matrix
Х	Pointer to REAL array
у	Pointer to REAL array

## **Author**

Chensong Zhang

Date

04/27/2013

Definition at line 117 of file blas\_str.c.

9.17.2.3 INT fasp\_dstr\_diagscale ( dSTRmat \* A, dSTRmat \* B )

 $B=D^{\setminus}\{-1\}A$ .

## **Parameters**

Α	Pointer to a 'dSTRmat' type matrix A
В	Pointer to a 'dSTRmat' type matrix B

#### **Author**

Shiquan Zhang

Date

2010/10/15

Modified by Chunsheng Feng, Zheng Li

Date

08/30/2012

Definition at line 142 of file blas\_str.c.

# 9.18 blas\_vec.c File Reference

## BLAS operations for vectors.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

```
    void fasp_blas_dvec_axpy (const REAL a, dvector *x, dvector *y)
```

```
y = a * x + y
```

void fasp\_blas\_dvec\_axpyz (const REAL a, dvector \*x, dvector \*y, dvector \*z)

z = a\*x + y, z is a third vector (z is cleared)

REAL fasp\_blas\_dvec\_dotprod (dvector \*x, dvector \*y)

Inner product of two vectors (x,y)

REAL fasp\_blas\_dvec\_relerr (dvector \*x, dvector \*y)

Relative error of two dvector x and y.

REAL fasp\_blas\_dvec\_norm1 (dvector \*x)

L1 norm of dvector x.

REAL fasp\_blas\_dvec\_norm2 (dvector \*x)

L2 norm of dvector x.

REAL fasp\_blas\_dvec\_norminf (dvector \*x)

Linf norm of dvector x.

## 9.18.1 Detailed Description

BLAS operations for vectors.

Definition in file blas vec.c.

## 9.18.2 Function Documentation

9.18.2.1 void fasp\_blas\_dvec\_axpy ( const REAL a, dvector \* x, dvector \* y )

y = a\*x + y

## **Parameters**

а	REAL factor a
X	Pointer to dvector x
У	Pointer to dvector y

**Author** 

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 35 of file blas vec.c.

9.18.2.2 void fasp\_blas\_dvec\_axpyz ( const REAL a, dvector \* x, dvector \* y, dvector \* z )

z = a\*x + y, z is a third vector (z is cleared)

## **Parameters**

а	REAL factor a
X	Pointer to dvector x
у	Pointer to dvector y
Z	Pointer to dvector z

**Author** 

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 87 of file blas\_vec.c.

9.18.2.3 REAL fasp\_blas\_dvec\_dotprod ( dvector \* x, dvector \* y )

Inner product of two vectors (x,y)

## **Parameters**

X	Pointer to dvector x
у	Pointer to dvector y

Returns

Inner product

**Author** 

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 123 of file blas\_vec.c.

9.18.2.4 REAL fasp\_blas\_dvec\_norm1 ( dvector \* x )

L1 norm of dvector x.

**Parameters** 

x Pointer to dvector x	
------------------------	--

Returns

L1 norm of x

**Author** 

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 224 of file blas\_vec.c.

9.18.2.5 **REAL** fasp\_blas\_dvec\_norm2 ( dvector \* x )

L2 norm of dvector x.

**Parameters** 

x Pointer to dvector x

Returns

L2 norm of x

**Author** 

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 267 of file blas\_vec.c.

9.18.2.6 REAL fasp\_blas\_dvec\_norminf ( dvector \* x )

Linf norm of dvector x.

**Parameters** 

x Pointer to dvector x

Returns

L\_inf norm of x

Author

Chensong Zhang

Date

07/01/209

Definition at line 307 of file blas\_vec.c.

9.18.2.7 REAL fasp\_blas\_dvec\_relerr ( dvector \* x, dvector \* y )

Relative error of two dvector x and y.

## **Parameters**

X	Pointer to dvector x
у	Pointer to dvector y

#### Returns

```
relative error ||x-y||/||x||
```

#### **Author**

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 169 of file blas\_vec.c.

# 9.19 checkmat.c File Reference

## Check matrix properties.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

INT fasp\_check\_diagpos (dCSRmat \*A)

Check positivity of diagonal entries of a CSR sparse matrix.

SHORT fasp\_check\_diagzero (dCSRmat \*A)

Check wether a CSR sparse matrix has diagonal entries that are very close to zero.

INT fasp\_check\_diagdom (dCSRmat \*A)

Check whether a matrix is diagonal dominant.

INT fasp\_check\_symm (dCSRmat \*A)

Check symmetry of a sparse matrix of CSR format.

SHORT fasp\_check\_dCSRmat (dCSRmat \*A)

Check whether an dCSRmat matrix is valid or not.

SHORT fasp\_check\_iCSRmat (iCSRmat \*A)

Check whether an iCSRmat matrix is valid or not.

# 9.19.1 Detailed Description

Check matrix properties.

Definition in file checkmat.c.

## 9.19.2 Function Documentation

9.19.2.1 SHORT fasp\_check\_dCSRmat ( dCSRmat \* A )

Check whether an dCSRmat matrix is valid or not.

**Parameters** 

A Pointer to the matrix in dCSRmat format

**Author** 

Shuo Zhang

Date

03/29/2009

Definition at line 276 of file checkmat.c.

9.19.2.2 INT fasp\_check\_diagdom ( dCSRmat \* A )

Check whether a matrix is diagonal dominant.

INT fasp\_check\_diagdom (dCSRmat \*A)

**Parameters** 

A Pointer to the dCSRmat matrix

#### Returns

Number of the rows which are diagonal dominant

Note

The routine chechs whether the sparse matrix is diagonal dominant on every row. It will print out the percentage of the rows which are diagonal dominant and which are not; the routine will return the number of the rows which are diagonal dominant.

**Author** 

Shuo Zhang

Date

03/29/2009

Definition at line 109 of file checkmat.c.

9.19.2.3 INT fasp\_check\_diagpos ( dCSRmat \* A )

Check positivity of diagonal entries of a CSR sparse matrix.

**Parameters** 

A Pointer to dCSRmat matrix

Returns

Number of negative diagonal entries

**Author** 

Shuo Zhang

Date

03/29/2009

Definition at line 27 of file checkmat.c.

9.19.2.4 SHORT fasp\_check\_diagzero ( dCSRmat \* A )

Check wether a CSR sparse matrix has diagonal entries that are very close to zero.

**Parameters** 

A pointr to the dCSRmat matrix

Returns

SUCCESS if no diagonal entry is clase to zero, else ERROR (negative value)

**Author** 

Shuo Zhang

Date

03/29/2009

Definition at line 64 of file checkmat.c.

9.19.2.5 SHORT fasp\_check\_iCSRmat ( iCSRmat \* A )

Check whether an iCSRmat matrix is valid or not.

**Parameters** 

A Pointer to the matrix in iCSRmat format

**Author** 

Shuo Zhang

Date

03/29/2009

Definition at line 310 of file checkmat.c.

9.19.2.6 INT fasp\_check\_symm ( dCSRmat \* A )

Check symmetry of a sparse matrix of CSR format.

#### **Parameters**

A Pointer to the dCSRmat matrix

#### Returns

1 and 2 if the structure of the matrix is not symmetric; 0 if the structure of the matrix is symmetric,

Note

Print the maximal relative difference between matrix and its transpose.

**Author** 

Shuo Zhang

Date

03/29/2009

Definition at line 154 of file checkmat.c.

# 9.20 coarsening\_cr.c File Reference

Coarsening with Brannick-Falgout strategy.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

• INT fasp\_amg\_coarsening\_cr (INT i\_0, INT i\_n, dCSRmat \*A, ivector \*vertices, AMG\_param \*param) CR coarsening.

# 9.20.1 Detailed Description

Coarsening with Brannick-Falgout strategy.

Definition in file coarsening\_cr.c.

## 9.20.2 Function Documentation

```
9.20.2.1 INT fasp_amg_coarsening_cr ( INT i_0, INT i_n, dCSRmat * A, ivector * vertices, AMG_param * param )
```

CR coarsening.

## **Parameters**

i_0	Starting index
i_n	Ending index
Α	Pointer to dCSRmat: the coefficient matrix (index starts from 0)
vertices	Pointer to CF, 0: fpt (current level) or 1: cpt
param	Pointer to AMG_param: AMG parameters

#### **Author**

James Brannick

Date

04/21/2010

Modified by Chunsheng Feng, Zheng Li

Date

10/14/2012

#### **CR STAGES**

Definition at line 41 of file coarsening\_cr.c.

# 9.21 coarsening\_rs.c File Reference

Coarsening with a modified Ruge-Stuben strategy.

```
#include "fasp.h"
#include "fasp_functs.h"
#include "linklist.inl"
```

## **Functions**

• INT fasp\_amg\_coarsening\_rs (dCSRmat \*A, ivector \*vertices, dCSRmat \*P, iCSRmat \*S, AMG\_param \*param) Standard and aggressive coarsening schemes.

## 9.21.1 Detailed Description

Coarsening with a modified Ruge-Stuben strategy.

Note

Ref Multigrid by U. Trottenberg, C. W. Oosterlee and A. Schuller Appendix P475 A.7 (by A. Brandt, P. Oswald and K. Stuben) Academic Press Inc., San Diego, CA, 2001.

Definition in file coarsening\_rs.c.

# 9.21.2 Function Documentation

9.21.2.1 INT fasp\_amg\_coarsening\_rs ( dCSRmat \* A, ivector \* vertices, dCSRmat \* P, iCSRmat \* S, AMG\_param \* param )

Standard and aggressive coarsening schemes.

#### **Parameters**

Α	Pointer to dCSRmat: Coefficient matrix (index starts from 0)
vertices	Indicator vector for the C/F splitting of the variables
Р	Interpolation matrix (nonzero pattern only)
S	Strong connection matrix
param	Pointer to AMG_param: AMG parameters

### Returns

SUCCESS or error message

#### **Author**

Xuehai Huang, Chensong Zhang, Xiaozhe Hu, Ludmil Zikatanov

Date

09/06/2010

Note

```
vertices = 0: fine; 1: coarse; 2: isolated or special
```

Modified by Xiaozhe Hu on 05/23/2011: add strength matrix as an argument Modified by Xiaozhe Hu on 04/24/2013: modfiy aggressive coarsening Modified by Chensong Zhang on 04/28/2013: remove linked list Modified by Chensong Zhang on 05/11/2013: restructure the code

Definition at line 56 of file coarsening\_rs.c.

## 9.22 convert.c File Reference

Some utilities for format conversion.

```
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

• unsigned long fasp\_aux\_change\_endian4 (unsigned long x)

Swap order for different endian systems.

double fasp\_aux\_change\_endian8 (double x)

Swap order for different endian systems.

• double fasp\_aux\_bbyteToldouble (unsigned char bytes[])

Swap order of double-precision float for different endian systems.

INT endian\_convert\_int (const INT inum, const INT illength, const INT endianflag)

Swap order of an INT number.

REAL endian\_convert\_real (const REAL rnum, INT vlength, INT endianflag)

Swap order of a REAL number.

# 9.22.1 Detailed Description

Some utilities for format conversion.

Definition in file convert.c.

## 9.22.2 Function Documentation

9.22.2.1 INT endian\_convert\_int ( const INT inum, const INT ilength, const INT endianflag )

Swap order of an INT number.

## **Parameters**

ſ	inum	An INT value
Ī	ilength	Length of INT: 2 for short, 4 for int, 8 for long
endianflag If endianflag = 1, it returns inum itself If endianflag = 2, it returns the swapped in		If endianflag = 1, it returns inum itself If endianflag = 2, it returns the swapped inum

#### **Returns**

Value of inum or swapped inum

**Author** 

Ziteng Wang

Date

2012-12-24

Definition at line 105 of file convert.c.

9.22.2.2 REAL endian\_convert\_real ( const REAL rnum, INT ilength, INT endianflag )

Swap order of a REAL number.

## **Parameters**

rnum	An REAL value
ilength	Length of INT: 2 for short, 4 for int, 8 for long
endianflag	If endianflag = 1, it returns rnum itself If endianflag = 2, it returns the swapped rnum

## Returns

Value of rnum or swapped rnum

Author

Ziteng Wang

Date

2012-12-24

Definition at line 137 of file convert.c.

9.22.2.3 double fasp\_aux\_bbyteToldouble ( unsigned char bytes[] )

Swap order of double-precision float for different endian systems.

## **Parameters**

bytes	A unsigned char
27.00	7. di 10.gi 10 di 01.di

Returns

Unsigend long ineger after swapping

**Author** 

Chensong Zhang

Date

11/16/2009

Definition at line 74 of file convert.c.

9.22.2.4 unsigned long fasp\_aux\_change\_endian4 (unsigned long x)

Swap order for different endian systems.

**Parameters** 

Х	An unsigned long integer
---	--------------------------

Returns

Unsigend long ineger after swapping

**Author** 

Chensong Zhang

Date

11/16/2009

Definition at line 25 of file convert.c.

9.22.2.5 double fasp\_aux\_change\_endian8 ( double x )

Swap order for different endian systems.

**Parameters** 

Х	A unsigned long integer

Returns

Unsigend long ineger after swapping

**Author** 

Chensong Zhang

Date

11/16/2009

Definition at line 43 of file convert.c.

# 9.23 doxygen.h File Reference

Main page for Doygen documentation.

# 9.23.1 Detailed Description

Main page for Doygen documentation.

Definition in file doxygen.h.

# 9.24 eigen.c File Reference

Simple subroutines for compute the extreme eigenvalues.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

REAL fasp\_dcsr\_eig (dCSRmat \*A, const REAL tol, const INT maxit)
 Approximate the largest eigenvalue of A by the power method.

# 9.24.1 Detailed Description

Simple subroutines for compute the extreme eigenvalues.

Definition in file eigen.c.

## 9.24.2 Function Documentation

```
9.24.2.1 REAL fasp_dcsr_eig ( dCSRmat * A, const REAL tol, const INT maxit )
```

Approximate the largest eigenvalue of A by the power method.

## **Parameters**

Α	Pointer to the dCSRmat matrix
tol	Tolerance for stopping the power method
maxit	Max number of iterations

#### **Returns**

Largest eigenvalue

**Author** 

Xiaozhe Hu

Date

01/25/2011

Definition at line 29 of file eigen.c.

# 9.25 factor.f File Reference

LU factoraization for CSR matrix.

# **Functions/Subroutines**

- subroutine **sfactr** (ia, ja, n, iu, ju, ip, nwku)
- subroutine **sfactr\_new** (ia, ja, n, iu, ju, ip, nwku, mem\_chk)
- subroutine **factor** (ia, ja, n, iu, ju, ip, iup, an, ad, un, di)
- subroutine **forbac** (iu, ju, un, di, n, x)

# 9.25.1 Detailed Description

LU factoraization for CSR matrix.

**Author** 

Ludmil Zikatanov

Date

01/01/2002

Definition in file factor.f.

# 9.26 famg.c File Reference

full AMG method as an iterative solver (main file)

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

```
    void fasp_solver_famg (dCSRmat *A, dvector *b, dvector *x, AMG_param *param)
    Solve Ax=b by full AMG.
```

## 9.26.1 Detailed Description

full AMG method as an iterative solver (main file)

Definition in file famg.c.

## 9.26.2 Function Documentation

```
9.26.2.1 void fasp_solver_famg ( dCSRmat * A, dvector * b, dvector * x, AMG_param * param )
```

Solve Ax=b by full AMG.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
Х	Pointer to dvector: the unknowns
param	Pointer to AMG_param: AMG parameters

### **Author**

Xiaozhe Hu

Date

02/27/2011

Modified by Chensong Zhang on 01/10/2012 Modified by Chensong Zhang on 05/05/2013: Remove error handling for AMG setup

Definition at line 31 of file famg.c.

# 9.27 fasp.h File Reference

## Main header file for FASP.

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include "messages.h"
```

## **Data Structures**

struct ddenmat

Dense matrix of REAL type.

· struct idenmat

Dense matrix of INT type.

struct dCSRmat

Sparse matrix of REAL type in CSR format.

struct iCSRmat

Sparse matrix of INT type in CSR format.

struct dCOOmat

Sparse matrix of REAL type in COO (or IJ) format.

struct iCOOmat

Sparse matrix of INT type in COO (or IJ) format.

struct dCSRLmat

Sparse matrix of REAL type in CSRL format.

struct dSTRmat

Structure matrix of REAL type.

struct dvector

Vector with n entries of REAL type.

· struct ivector

Vector with n entries of INT type.

struct ILU\_param

Parameters for ILU.

struct ILU\_data

Data for ILU setup.

struct Schwarz param

Parameters for Schwarz method.

· struct Schwarz\_data

Data for Schwarz methods.

struct AMG\_param

Parameters for AMG solver.

· struct AMG data

Data for AMG solvers.

struct precond\_data

Data passed to the preconditioners.

struct precond\_data\_str

Data passed to the preconditioner for dSTRmat matrices.

· struct precond\_diagstr

Data passed to diagnal preconditioner for dSTRmat matrices.

· struct precond

Preconditioner data and action.

· struct mxv matfree

Matrix-vector multiplication, replace the actual matrix.

struct input\_param

Input parameters.

struct itsolver\_param

Parameters passed to iterative solvers.

struct grid2d

Two dimensional grid data structure.

struct Link

Struct for Links.

struct linked\_list

A linked list node.

#### **Macros**

- #define FASP HEADER
- #define DEBUG MODE OFF

Flags for developer's use only.

- #define CHMEM\_MODE OFF
- #define DIAGONAL PREF OFF
- #define FASP USE ILU ON

For external software package support.

- #define DLMALLOC OFF
- #define NEDMALLOC OFF
- #define SHORT short

For Fortran compatibilty.

- #define INT int
- · #define LONG long
- #define REAL double
- #define BIGREAL 1e+20

Some global constants.

- #define SMALLREAL 1e-20
- #define MAX REFINE LVL 20
- #define MAX AMG LVL 20
- #define STAG RATIO 1e-4
- #define MAX\_STAG 20
- #define MAX RESTART 20
- #define OPENMP\_HOLDS 2000
- #define MAX(a, b) (((a)>(b))?(a):(b))

Definition of max, min, abs.

- #define MIN(a, b) (((a)<(b))?(a):(b))</li>
- #define ABS(a) (((a)>=0.0)?(a):-(a))
- #define GT(a, b) (((a)>(b))?(TRUE):(FALSE))

Definition of >, >=, <, <=, and isnan.

- #define GE(a, b) (((a)>=(b))?(TRUE):(FALSE))
- #define LS(a, b) (((a)<(b))?(TRUE):(FALSE))
- #define LE(a, b) (((a)<=(b))?(TRUE):(FALSE))</li>
- #define ISNAN(a) (((a)!=(a))?(TRUE):(FALSE))
- #define ISTART 0

Index starting point: C convention or Fortran convention.

- #define N2C(ind) ((ind)-ISTART)
- #define C2N(ind) ((ind)+ISTART)
- #define FASP GSRB 1

# **Typedefs**

- · typedef struct ddenmat ddenmat
- · typedef struct idenmat idenmat
- typedef struct dCSRmat dCSRmat
- typedef struct iCSRmat iCSRmat
- typedef struct dCOOmat dCOOmat
- typedef struct iCOOmat iCOOmat

- typedef struct dCSRLmat dCSRLmat
- typedef struct dSTRmat dSTRmat
- typedef struct dvector dvector
- · typedef struct ivector ivector
- typedef struct grid2d grid2d
- typedef grid2d \* pgrid2d
- typedef const grid2d \* pcgrid2d
- typedef struct linked list ListElement
- typedef ListElement \* LinkList

#### **Variables**

- unsigned INT total\_alloc\_mem
- unsigned INT total\_alloc\_count
- INT nx rb
- INT ny\_rb
- INT nz\_rb
- INT \* IMAP
- INT MAXIMAP

## 9.27.1 Detailed Description

Main header file for FASP. This header file contains general constants and data structures used in FASP.

Note

Only define macros and data structures, no function decorations.

Created by Chensong Zhang on 08/12/2010. Modified by Chensong Zhang on 12/13/2011.

Modified by Chensong Zhang on 12/25/2011.

Definition in file fasp.h.

9.27.2 Macro Definition Documentation

9.27.2.1 #define \_\_FASP\_HEADER\_\_

indicate fasp.h has been included before

Definition at line 23 of file fasp.h.

9.27.2.2 #define ABS( a)(((a)>=0.0)?(a):-(a))

absolute value of a

Definition at line 72 of file fasp.h.

9.27.2.3 #define BIGREAL 1e+20

Some global constants.

A large real number

Definition at line 58 of file fasp.h.

9.27.2.4 #define C2N( ind ) ((ind)+ISTART)

map from C index 0,1,... to Natural index 1,2,...

Definition at line 88 of file fasp.h.

9.27.2.5 #define CHMEM\_MODE OFF

output MEMORY usage information

Definition at line 35 of file fasp.h.

9.27.2.6 #define DEBUG\_MODE OFF

Flags for developer's use only.

output DEBUG information

Definition at line 33 of file fasp.h.

9.27.2.7 #define DIAGONAL\_PREF OFF

order each row such that diagonal appears first

Definition at line 38 of file fasp.h.

9.27.2.8 #define DLMALLOC OFF

use dimalloc instead of standard malloc

Definition at line 44 of file fasp.h.

9.27.2.9 #define FASP\_GSRB 1

MG level 0 use RedBlack Gauss Seidel Smoothing

Definition at line 1076 of file fasp.h.

9.27.2.10 #define FASP\_USE\_ILU ON

For external software package support.

enable ILU or not

Definition at line 43 of file fasp.h.

9.27.2.11 #define GE( a, b) (((a)>=(b))?(TRUE):(FALSE))

is  $a \ge b$ ?

Definition at line 78 of file fasp.h.

9.27.2.12 #define GT( a, b) (((a)>(b))?(TRUE):(FALSE))

Definition of >, >=, <, <=, and isnan.

is a > b?

Definition at line 77 of file fasp.h.

9.27.2.13 #define INT int

regular integer type: int or long

Definition at line 51 of file fasp.h.

9.27.2.14 #define ISNAN( a) (((a)!=(a))?(TRUE):(FALSE))

is a == NAN?

Definition at line 81 of file fasp.h.

9.27.2.15 #define ISTART 0

Index starting point: C convention or Fortran convention.

0 if in Natural index, 1 if data is in C index

Definition at line 86 of file fasp.h.

9.27.2.16 #define LE( a, b) (((a)<=(b))?(TRUE):(FALSE))

is a  $\leq$ = b?

Definition at line 80 of file fasp.h.

9.27.2.17 #define LONG long

long integer type

Definition at line 52 of file fasp.h.

9.27.2.18 #define LS( a, b) (((a)<(b))?(TRUE):(FALSE))

is a < b?

Definition at line 79 of file fasp.h.

9.27.2.19 #define MAX( a, b) (((a)>(b))?(a):(b))

Definition of max, min, abs.

bigger one in a and b

Definition at line 70 of file fasp.h.

9.27.2.20 #define MAX\_AMG\_LVL 20

Maximal AMG coarsening level

Definition at line 61 of file fasp.h.

9.27.2.21 #define MAX\_REFINE\_LVL 20

Maximal refinement level

Definition at line 60 of file fasp.h.

9.27.2.22 #define MAX\_RESTART 20

Maximal number of restarting

Definition at line 64 of file fasp.h.

9.27.2.23 #define MAX\_STAG 20

Maximal number of staganation times

Definition at line 63 of file fasp.h.

9.27.2.24 #define MIN( a, b) (((a)<(b))?(a):(b))

smaller one in a and b

Definition at line 71 of file fasp.h.

9.27.2.25 #define N2C( ind ) ((ind)-ISTART)

map from Natural index 1,2,... to C index 0,1,...

Definition at line 87 of file fasp.h.

9.27.2.26 #define NEDMALLOC OFF

use nedmalloc instead of standard malloc

Definition at line 45 of file fasp.h.

9.27.2.27 #define OPENMP\_HOLDS 2000

Switch to sequence or openmp

Definition at line 65 of file fasp.h.

9.27.2.28 #define REAL double

float type

Definition at line 53 of file fasp.h.

9.27.2.29 #define SHORT short

For Fortran compatibilty.

short integer type

Definition at line 50 of file fasp.h.

9.27.2.30 #define SMALLREAL 1e-20

A small real number

Definition at line 59 of file fasp.h.

9.27.2.31 #define STAG\_RATIO 1e-4

Staganation tolerance = tol\*STAGRATIO

Definition at line 62 of file fasp.h.

9.27.3 Typedef Documentation

9.27.3.1 typedef struct dCOOmat dCOOmat

Sparse matrix of REAL type in COO format

9.27.3.2 typedef struct dCSRLmat dCSRLmat

Sparse matrix of REAL type in CSRL format

9.27.3.3 typedef struct dCSRmat dCSRmat

Sparse matrix of REAL type in CSR format

9.27.3.4 typedef struct ddenmat ddenmat

Dense matrix of REAL type

9.27.3.5 typedef struct dSTRmat dSTRmat

Structured matrix of REAL type

9.27.3.6 typedef struct dvector dvector

Vector of REAL type

9.27.3.7 typedef struct grid2d grid2d

2D grid type for plotting

9.27.3.8 typedef struct iCOOmat iCOOmat

Sparse matrix of INT type in COO format

9.27.3.9 typedef struct iCSRmat iCSRmat

Sparse matrix of INT type in CSR format

9.27.3.10 typedef struct idenmat idenmat

Dense matrix of INT type

9.27.3.11 typedef struct ivector ivector

Vector of INT type

9.27.3.12 typedef ListElement\* LinkList

List of linkslinked list

Definition at line 1071 of file fasp.h.

9.27.3.13 typedef struct linked\_list ListElement

Linked element in list

9.27.3.14 typedef const grid2d\* pcgrid2d

Grid in 2d

Definition at line 1025 of file fasp.h.

9.27.3.15 typedef grid2d\* pgrid2d

Grid in 2d

Definition at line 1023 of file fasp.h.

9.27.4 Variable Documentation

9.27.4.1 **INT**\* IMAP

Red Black Gs Smoother imap

9.27.4.2 INT MAXIMAP

Red Black Gs Smoother max dofs of reservoir

9.27.4.3 INT nx\_rb

Red Black Gs Smoother Nx

9.27.4.4 INT ny\_rb

Red Black Gs Smoother Ny

9.27.4.5 INT nz\_rb

Red Black Gs Smoother Nz

9.27.4.6 unsigned INT total\_alloc\_count

total allocation times

Definition at line 33 of file memory.c.

9.27.4.7 unsigned INT total\_alloc\_mem

total allocated memory

Definition at line 32 of file memory.c.

# 9.28 fasp\_block.h File Reference

Main header file for FASP (block matrices)

#include "fasp.h"

### **Data Structures**

struct dBSRmat

Block sparse row storage matrix of REAL type.

struct block dCSRmat

Block REAL CSR matrix format.

struct block iCSRmat

Block INT CSR matrix format.

struct block dvector

Block REAL vector structure.

struct block\_ivector

Block INT vector structure.

struct block Reservoir

Block REAL matrix format for reservoir simulation.

struct block\_BSR

Block REAL matrix format for reservoir simulation.

struct AMG\_data\_bsr

Data for multigrid levels. (BSR format)

· struct precond diagbsr

Data passed to diagnal preconditioner for dBSRmat matrices.

struct precond\_data\_bsr

Data passed to the preconditioners.

· struct precond\_block\_reservoir\_data

Data passed to the preconditioner for preconditioning reservoir simulation problems.

struct precond\_block\_data

Data passed to the preconditioner for block diagonal preconditioning.

· struct precond FASP blkoil data

Data passed to the preconditioner for preconditioning reservoir simulation problems.

# **Typedefs**

- typedef struct dBSRmat dBSRmat
- typedef struct block\_dCSRmat block\_dCSRmat
- typedef struct block\_iCSRmat block\_iCSRmat
- typedef struct block\_dvector block\_dvector
- · typedef struct block ivector block ivector
- typedef struct block\_Reservoir block\_Reservoir
- typedef struct block\_BSR block\_BSR
- typedef struct precond\_block\_reservoir\_data precond\_block\_reservoir\_data

## 9.28.1 Detailed Description

Main header file for FASP (block matrices)

Note

This header file contains definitions of block matrices, including grid-major type and variable-major type. In this header, we only define macros and data structures, not function decorations.

Created by Chensong Zhang on 05/21/2010. Modified by Xiaozhe Hu on 05/28/2010: add precond\_block\_reservoir\_data. Modified by Xiaozhe Hu on 06/15/2010: modify precond\_block\_reservoir\_data. Modified by Chensong Zhang on 10/11/2010: add BSR data.

Modified by Chensong Zhang on 10/17/2012: modify comments.

Definition in file fasp\_block.h.

9.28.2 Typedef Documentation

9.28.2.1 typedef struct block BSR block BSR

Block of BSR matrices of REAL type

9.28.2.2 typedef struct block\_dCSRmat block\_dCSRmat

Matrix of REAL type in Block CSR format

9.28.2.3 typedef struct block\_dvector block\_dvector

Vector of REAL type in Block format

9.28.2.4 typedef struct block\_iCSRmat block\_iCSRmat

Matrix of INT type in Block CSR format

9.28.2.5 typedef struct block\_ivector block\_ivector

Vector of INT type in Block format

9.28.2.6 typedef struct block\_Reservoir block\_Reservoir

Special block matrix for Reservoir Simulation

9.28.2.7 typedef struct dBSRmat dBSRmat

Matrix of REAL type in BSR format

9.28.2.8 typedef struct precond\_block\_reservoir\_data precond\_block\_reservoir\_data

Precond data for Reservoir Simulation

# 9.29 fmgcycle.c File Reference

Abstract non-recursive full multigrid cycle.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "forts_ns.h"
#include "mg_util.inl"
```

#### **Functions**

void fasp\_solver\_fmgcycle (AMG\_data \*mgl, AMG\_param \*param)
 Solve Ax=b with non-recursive full multigrid K-cycle.

#### 9.29.1 Detailed Description

Abstract non-recursive full multigrid cycle.

Definition in file fmgcycle.c.

#### 9.29.2 Function Documentation

```
9.29.2.1 void fasp_solver_fmgcycle ( AMG data * mgl, AMG param * param )
```

Solve Ax=b with non-recursive full multigrid K-cycle.

#### **Parameters**

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

#### **Author**

Chensong Zhang

Date

02/27/2011

Modified by Chensong Zhang on 06/01/2012: fix a bug when there is only one level. Modified by Chensong Zhang on 02/27/2013: update direct solvers.

Definition at line 34 of file fmgcycle.c.

#### 9.30 formats.c File Reference

Matrix format conversion routines.

```
#include "fasp.h"
#include "fasp_block.h"
#include "fasp_functs.h"
```

#### **Functions**

SHORT fasp\_format\_dcoo\_dcsr (dCOOmat \*A, dCSRmat \*B)

Transform a REAL matrix from its IJ format to its CSR format.

SHORT fasp format dcsr dcoo (dCSRmat \*A, dCOOmat \*B)

Transform a REAL matrix from its CSR format to its IJ format.

SHORT fasp format dstr dcsr (dSTRmat \*A, dCSRmat \*B)

Transfer a 'dSTRmat' type matrix into a 'dCSRmat' type matrix.

dCSRmat fasp\_format\_bdcsr\_dcsr (block\_dCSRmat \*Ab)

Form the whole dCSRmat A using blocks given in Ab.

dCSRLmat \* fasp\_format\_dcsrl\_dcsr (dCSRmat \*A)

Convert a dCSRmat into a dCSRLmat.

dCSRmat fasp\_format\_dbsr\_dcsr (dBSRmat \*B)

Transfer a 'dBSRmat' type matrix into a dCSRmat.

dBSRmat fasp\_format\_dcsr\_dbsr (dCSRmat \*B, const INT nb)

Transfer a dCSRmat type matrix into a dBSRmat.

dBSRmat fasp\_format\_dstr\_dbsr (dSTRmat \*B)

Transfer a 'dSTRmat' type matrix to a 'dBSRmat' type matrix.

dCOOmat \* fasp\_format\_dbsr\_dcoo (dBSRmat \*B)

Transfer a 'dBSRmat' type matrix to a 'dCOOmat' type matrix.

# 9.30.1 Detailed Description

Matrix format conversion routines.

Definition in file formats.c.

#### 9.30.2 Function Documentation

9.30.2.1 dCSRmat fasp\_format\_bdcsr\_dcsr ( block\_dCSRmat \* Ab )

Form the whole dCSRmat A using blocks given in Ab.

**Parameters** 

Ab Pointer to block\_dCSRmat matrix

Returns

dCSRmat matrix if succeed, NULL if fail

**Author** 

Shiquan Zhang

Date

08/10/2010

Definition at line 293 of file formats.c.

9.30.2.2 dCOOmat \* fasp\_format\_dbsr\_dcoo ( dBSRmat \* B )

Transfer a 'dBSRmat' type matrix to a 'dCOOmat' type matrix.

**Parameters** 

B Pointer to dBSRmat matrix

Returns

Pointer to dCOOmat matrix

**Author** 

Zhiyang Zhou

Date

2010/10/26

Definition at line 956 of file formats.c.

9.30.2.3 dCSRmat fasp\_format\_dbsr\_dcsr ( dBSRmat \* B )

Transfer a 'dBSRmat' type matrix into a dCSRmat.

**Parameters** 

B Pointer to dBSRmat matrix

Returns

dCSRmat matrix

Author

Zhiyang Zhou

Date

10/23/2010

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/24/2012

Note

Works for general nb (Xiaozhe)

Definition at line 496 of file formats.c.

9.30.2.4 SHORT fasp\_format\_dcoo\_dcsr ( dCOOmat \* A, dCSRmat \* B )

Transform a REAL matrix from its IJ format to its CSR format.

**Parameters** 

Α	Pointer to dCOOmat matrix
В	Pointer to dCSRmat matrix

Returns

SUCCESS if succeed

**Author** 

Xuehai Huang

Date

08/10/2009

Definition at line 28 of file formats.c.

9.30.2.5 dBSRmat fasp\_format\_dcsr\_dbsr ( dCSRmat \* B, const INT nb )

Transfer a dCSRmat type matrix into a dBSRmat.

#### **Parameters**

В	Pointer to the dCSRmat type matrix
nb	size of each block

Returns

dBSRmat matrix

**Author** 

Changhe Qiao

Date

03/12/2012

Modified by Xiaozhe Hu on 03/13/2012 Modified by Chunsheng Feng, Zheng Li on 10/13/2012 Definition at line 721 of file formats.c.

9.30.2.6 SHORT fasp\_format\_dcsr\_dcoo ( dCSRmat \* A, dCOOmat \* B )

Transform a REAL matrix from its CSR format to its IJ format.

#### **Parameters**

Α	Pointer to dCSRmat matrix
В	Pointer to dCOOmat matrix

Returns

SUCCESS if succeed

**Author** 

Xuehai Huang

Date

08/10/2009

Modified by Chunsheng Feng, Zheng Li

Date

10/12/2012

Definition at line 81 of file formats.c.

9.30.2.7 dCSRLmat \* fasp\_format\_dcsrl\_dcsr ( dCSRmat \* A )

Convert a dCSRmat into a dCSRLmat.

**Parameters** 

A Pointer to dCSRLmat matrix

Returns

Pointer to dCSRLmat matrix

Author

Zhiyang Zhou

Date

2011/01/07

Definition at line 362 of file formats.c.

9.30.2.8 dBSRmat fasp\_format\_dstr\_dbsr ( dSTRmat \* B )

Transfer a 'dSTRmat' type matrix to a 'dBSRmat' type matrix.

**Parameters** 

B Pointer to dSTRmat matrix

Returns

dBSRmat matrix

Author

Zhiyang Zhou

Date

2010/10/26

Definition at line 852 of file formats.c.

9.30.2.9 SHORT fasp\_format\_dstr\_dcsr ( dSTRmat \* A, dCSRmat \* B )

Transfer a 'dSTRmat' type matrix into a 'dCSRmat' type matrix.

**Parameters** 

Α	Pointer to dSTRmat matrix
В	Pointer to dCSRmat matrix

Returns

SUCCESS if succeed

**Author** 

Zhiyang Zhou

Date

2010/04/29

Definition at line 118 of file formats.c.

# 9.31 givens.c File Reference

Givens transformation.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

• void fasp\_aux\_givens (const REAL beta, dCSRmat \*H, dvector \*y, REAL \*tmp)

Perform Givens rotations to compute y | beta\*e\_1- H\*y|.

## 9.31.1 Detailed Description

Givens transformation.

Definition in file givens.c.

## 9.31.2 Function Documentation

```
9.31.2.1 void fasp_aux_givens ( const REAL beta, dCSRmat * H, dvector * y, REAL * tmp )
```

Perform Givens rotations to compute y |beta\*e\_1- H\*y|.

#### **Parameters**

beta	Norm of residual r_0
Н	(m+1)*m upper Hessenberg dCSRmat matrix
У	Minimizer of  beta*e_1- H*y
tmp	Temporary work array

**Author** 

Xuehai Huang

Date

10/19/2008

Definition at line 28 of file givens.c.

# 9.32 gmg\_poisson.c File Reference

GMG method as an iterative solver for Poisson Problem.

```
#include <time.h>
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "gmg util.inl"
```

#### **Functions**

- INT fasp\_poisson\_gmg\_1D (REAL \*u, REAL \*b, INT nx, INT maxlevel, REAL rtol, const SHORT prtlvl)

  Solve Ax=b of Poisson 1D equation by Geometric Multigrid Method.
- INT fasp\_poisson\_gmg\_2D (REAL \*u, REAL \*b, INT nx, INT ny, INT maxlevel, REAL rtol, const SHORT prtlvl)

  Solve Ax=b of Poisson 2D equation by Geometric Multigrid Method.
- INT fasp\_poisson\_gmg\_3D (REAL \*u, REAL \*b, INT nx, INT ny, INT nz, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 3D equation by Geometric Multigrid Method.

- void fasp\_poisson\_fgmg\_1D (REAL \*u, REAL \*b, INT nx, INT maxlevel, REAL rtol, const SHORT prtlvl)

  Solve Ax=b of Poisson 1D equation by Geometric Multigrid Method (Full Multigrid)
- void fasp\_poisson\_fgmg\_2D (REAL \*u, REAL \*b, INT nx, INT ny, INT maxlevel, REAL rtol, const SHORT prtlvl)

  Solve Ax=b of Poisson 2D equation by Geometric Multigrid Method (Full Multigrid)
- void fasp\_poisson\_fgmg\_3D (REAL \*u, REAL \*b, INT nx, INT ny, INT nz, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 3D equation by Geometric Multigrid Method (Full Multigrid)

- INT fasp\_poisson\_pcg\_gmg\_1D (REAL \*u, REAL \*b, INT nx, INT maxlevel, REAL rtol, const SHORT prtlvl)

  Solve Ax=b of Poisson 1D equation by Geometric Multigrid Method (GMG preconditioned Conjugate Gradient method)
- INT fasp\_poisson\_pcg\_gmg\_2D (REAL \*u, REAL \*b, INT nx, INT ny, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 2D equation by Geometric Multigrid Method (GMG preconditioned Conjugate Gradient method)

 INT fasp\_poisson\_pcg\_gmg\_3D (REAL \*u, REAL \*b, INT nx, INT ny, INT nz, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 3D equation by Geometric Multigrid Method (GMG preconditioned Conjugate Gradient method)

## 9.32.1 Detailed Description

GMG method as an iterative solver for Poisson Problem.

Definition in file gmg poisson.c.

#### 9.32.2 Function Documentation

```
9.32.2.1 void fasp_poisson_fgmg_1D ( REAL * u, REAL * b, INT nx, INT maxlevel, REAL rtol, const SHORT prtlvl )
```

Solve Ax=b of Poisson 1D equation by Geometric Multigrid Method (Full Multigrid)

#### **Parameters**

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

**Author** 

Ziteng Wang

Date

06/07/2013

Definition at line 417 of file gmg poisson.c.

9.32.2.2 void fasp\_poisson\_fgmg\_2D ( REAL \* u, REAL \* b, INT nx, INT ny, INT maxlevel, REAL rtol, const SHORT prtlvl )

Solve Ax=b of Poisson 2D equation by Geometric Multigrid Method (Full Multigrid)

#### **Parameters**

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
ny	Number of grids in Y direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

**Author** 

Ziteng Wang

Date

06/07/2013

Definition at line 509 of file gmg\_poisson.c.

9.32.2.3 void fasp\_poisson\_fgmg\_3D ( REAL \* u, REAL \* b, INT nx, INT ny, INT nz, INT maxlevel, REAL rtol, const SHORT prtlvl )

Solve Ax=b of Poisson 3D equation by Geometric Multigrid Method (Full Multigrid)

#### **Parameters**

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
ny	NUmber of grids in y direction
nz	NUmber of grids in z direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

**Author** 

Ziteng Wang

Date

06/07/2013

Definition at line 616 of file gmg\_poisson.c.

9.32.2.4 INT fasp\_poisson\_gmg\_1D ( REAL \* u, REAL \* b, INT nx, INT maxlevel, REAL rtol, const SHORT prtlvl )

Solve Ax=b of Poisson 1D equation by Geometric Multigrid Method.

#### **Parameters**

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

**Author** 

Ziteng Wang

Date

06/07/2013

Definition at line 34 of file gmg\_poisson.c.

9.32.2.5 INT fasp\_poisson\_gmg\_2D ( REAL \* u, REAL \* b, INT nx, INT ny, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 2D equation by Geometric Multigrid Method.

#### **Parameters**

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
ny	Number of grids in y direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

Author

Ziteng Wang

Date

06/07/2013

Definition at line 154 of file gmg\_poisson.c.

9.32.2.6 INT fasp\_poisson\_gmg\_3D ( REAL \* u, REAL \* b, INT nx, INT ny, INT nz, INT maxlevel, REAL rtol, const SHORT prtlvl )

Solve Ax=b of Poisson 3D equation by Geometric Multigrid Method.

#### **Parameters**

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
ny	Number of grids in y direction
nz	Number of grids in z direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

Author

Ziteng Wang

**Date** 

06/07/2013

Definition at line 285 of file gmg\_poisson.c.

9.32.2.7 INT fasp\_poisson\_pcg\_gmg\_1D ( REAL \* u, REAL \* b, INT nx, INT maxlevel, REAL rtol, const SHORT prtlvl )

Solve Ax=b of Poisson 1D equation by Geometric Multigrid Method (GMG preconditioned Conjugate Gradient method)

#### **Parameters**

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

**Author** 

Ziteng Wang

Date

06/07/2013

Definition at line 723 of file gmg poisson.c.

9.32.2.8 INT fasp\_poisson\_pcg\_gmg\_2D ( REAL \* u, REAL \* b, INT nx, INT ny, INT maxlevel, REAL rtol, const SHORT prtlvl )

Solve Ax=b of Poisson 2D equation by Geometric Multigrid Method (GMG preconditioned Conjugate Gradient method)

#### **Parameters**

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
ny	Number of grids in y direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

**Author** 

Ziteng Wang

Date

06/07/2013

Definition at line 813 of file gmg\_poisson.c.

9.32.2.9 INT fasp\_poisson\_pcg\_gmg\_3D ( REAL \* u, REAL \* b, INT nx, INT ny, INT nz, INT maxlevel, REAL rtol, const SHORT prtlvl )

Solve Ax=b of Poisson 3D equation by Geometric Multigrid Method (GMG preconditioned Conjugate Gradient method)

#### **Parameters**

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
ny	Number of grids in y direction
nz	Number of grids in z direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

## Author

Ziteng Wang

Date

06/07/2013

Definition at line 918 of file gmg\_poisson.c.

# 9.33 gmg\_util.inl File Reference

Routines for GMG solvers.

# 9.33.1 Detailed Description

Routines for GMG solvers.

Definition in file gmg\_util.inl.

# 9.34 graphics.c File Reference

Functions for graphical output.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

- void fasp\_dcsr\_plot (const dCSRmat \*A, const char \*filename, INT size)
  - Write sparse matrix pattern in BMP file format.
- void fasp\_grid2d\_plot (pgrid2d pg, INT level)

Output grid to a EPS file.

# 9.34.1 Detailed Description

Functions for graphical output.

Definition in file graphics.c.

## 9.34.2 Function Documentation

9.34.2.1 void fasp\_dcsr\_plot ( const dCSRmat \* A, const char \* filename, INT size )

Write sparse matrix pattern in BMP file format.

#### **Parameters**

,	Pointer to the dCSRmat matrix	
filenam	e File name	
siz	e size*size is the picture size for the picture	

#### **Author**

Chensong Zhang

Date

03/29/2009

Note

The routine spm\_show\_mat writes pattern of the specified dCSRmat matrix in uncompressed BMP file format (Windows bitmap) to a binary file whose name is specified by the character string filename.

Each pixel corresponds to one matrix element. The pixel colors have the following meaning:

White structurally zero element Blue positive element Red negative element Brown nearly zero element Definition at line 44 of file graphics.c.

9.34.2.2 void fasp\_grid2d\_plot ( pgrid2d pg, INT level )

Output grid to a EPS file.

#### **Parameters**

pg	Pointer to grid in 2d
level	Number of levels

#### **Author**

Chensong Zhang

Date

03/29/2009

Definition at line 92 of file graphics.c.

## 9.35 ilu.f File Reference

ILU routines for preconditioning adapted from SPARSEKIT.

#### **Functions/Subroutines**

- subroutine iluk (n, a, ja, ia, lfil, alu, jlu, iwk, ierr, nzlu)
- subroutine ilut (n, a, ja, ia, lfil, droptol, alu, jlu, iwk, ierr, nz)
- subroutine ilutp (n, a, ja, ia, lfil, droptol, permtol, mbloc, alu, jlu, iwk, ierr, nz)
- subroutine **srtr** (num, q)
- subroutine **qsplit** (a, ind, n, ncut)
- subroutine symbfactor (n, colind, rwptr, levfill, nzmax, nzlu, ijlu, uptr, ierr)

## 9.35.1 Detailed Description

ILU routines for preconditioning adapted from SPARSEKIT.

Note

Incomplete Factorization Methods: ILUk, ILUt, ILUtp

Definition in file ilu.f.

# 9.36 ilu\_setup\_bsr.c File Reference

Setup Incomplete LU decomposition for dBSRmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

### **Functions**

- void symbfactor\_ (const INT \*n, INT \*colind, INT \*rwptr, const INT \*levfill, const INT \*nzmax, INT \*nzlu, INT \*ijlu, INT \*uptr, INT \*ierr)
- SHORT fasp\_ilu\_dbsr\_setup (dBSRmat \*A, ILU\_data \*iludata, ILU\_param \*iluparam)

Get ILU decoposition of a BSR matrix A.

## 9.36.1 Detailed Description

Setup Incomplete LU decomposition for dBSRmat matrices.

Definition in file ilu setup bsr.c.

- 9.36.2 Function Documentation
- $9.36.2.1 \quad \textbf{SHORT fasp\_ilu\_dbsr\_setup ( dBSRmat * \textit{A, ILU\_data} * \textit{iludata, ILU\_param} * \textit{iluparam} )}$

Get ILU decoposition of a BSR matrix A.

#### **Parameters**

Α	Pointer to dBSRmat matrix
iludata	Pointer to ILU_data
iluparam	Pointer to ILU_param

#### **Author**

Shiquan Zhang, Xiaozhe Hu

Date

11/08/2010

Note

Works for general nb (Xiaozhe)

Definition at line 42 of file ilu\_setup\_bsr.c.

# 9.37 ilu\_setup\_csr.c File Reference

Setup of ILU decomposition for dCSRmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

### **Functions**

- void iluk\_ (const INT \*n, REAL \*a, INT \*ja, INT \*ia, INT \*lfil, REAL \*alu, INT \*jlu, INT \*iwk, INT \*ierr, INT \*nzlu)
- void ilut\_ (const INT \*n, REAL \*a, INT \*ja, INT \*ia, INT \*lfil, const REAL \*droptol, REAL \*alu, INT \*jlu, INT \*iwk, INT \*ierr, INT \*nz)
- void ilutp\_ (const INT \*n, REAL \*a, INT \*ja, INT \*ia, INT \*lfil, const REAL \*droptol, const REAL \*permtol, const INT \*mbloc, REAL \*alu, INT \*jlu, INT \*iwk, INT \*ierr, INT \*nz)
- SHORT fasp\_ilu\_dcsr\_setup (dCSRmat \*A, ILU\_data \*iludata, ILU\_param \*iluparam)

Get ILU decoposition of a CSR matrix A.

# 9.37.1 Detailed Description

Setup of ILU decomposition for dCSRmat matrices.

Definition in file ilu\_setup\_csr.c.

#### 9.37.2 Function Documentation

9.37.2.1 SHORT fasp\_ilu\_dcsr\_setup ( dCSRmat \* A, ILU\_data \* iludata, ILU\_param \* iluparam )

Get ILU decoposition of a CSR matrix A.

#### **Parameters**

Α	Pointer to dCSRmat matrix
iludata	Pointer to ILU_data
iluparam	Pointer to ILU_param

#### **Author**

Shiquan Zhang

Date

12/27/2009

Definition at line 48 of file ilu\_setup\_csr.c.

# 9.38 ilu\_setup\_str.c File Reference

Setup of ILU decomposition for dSTRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

- void fasp\_ilu\_dstr\_setup0 (dSTRmat \*A, dSTRmat \*LU)
  - Get ILU(0) decomposition of a structured matrix A.
- void fasp\_ilu\_dstr\_setup1 (dSTRmat \*A, dSTRmat \*LU)

Get ILU(1) decoposition of a structured matrix A.

## 9.38.1 Detailed Description

Setup of ILU decomposition for dSTRmat matrices.

Definition in file ilu\_setup\_str.c.

## 9.38.2 Function Documentation

```
9.38.2.1 void fasp_ilu_dstr_setup0 ( dSTRmat * A, dSTRmat * LU )
```

Get ILU(0) decomposition of a structured matrix A.

**Parameters** 

Α	Pointer to dSTRmat
---	--------------------

LU	Pointer to ILU structured matrix of REAL type
----	---

**Author** 

Shiquan Zhang, Xiaozhe Hu

Date

11/08/2010

Note

Only works for 5 bands 2D and 7 bands 3D matrix with default offsets (order can be arbitrary)!

Definition at line 28 of file ilu\_setup\_str.c.

```
9.38.2.2 void fasp_ilu_dstr_setup1 ( dSTRmat * A, dSTRmat * LU )
```

Get ILU(1) decoposition of a structured matrix A.

#### **Parameters**

Α	Pointer to oringinal structured matrix of REAL type
LU	Pointer to ILU structured matrix of REAL type

## Author

Shiquan Zhang, Xiaozhe Hu

Date

11/08/2010

Note

put L and U in a STR matrix and it has the following structure: the diag is d, the offdiag of L are alpha1 to alpha6, the offdiag of U are beta1 to beta6

Only works for 5 bands 2D and 7 bands 3D matrix with default offsets

Definition at line 319 of file ilu\_setup\_str.c.

# 9.39 init.c File Reference

Initialize important data structures.

```
#include "fasp.h"
#include "fasp_functs.h"
```

9.39 init.c File Reference 171

#### **Functions**

AMG data \* fasp amg data create (SHORT max levels)

Create and initialize AMG\_data for classical and SA AMG.

AMG\_data\_bsr \* fasp\_amg\_data\_bsr\_create (SHORT max\_levels)

Create and initialize AMG\_data data sturcture for AMG/SAMG (BSR format)

• void fasp\_ilu\_data\_alloc (INT iwk, INT nwork, ILU\_data \*iludata)

Allocate workspace for ILU factorization.

void fasp\_schwarz\_data\_free (Schwarz\_data \*schwarz)

Free Schwarz data data memeory space.

void fasp\_amg\_data\_free (AMG\_data \*mgl, AMG\_param \*param)

Free AMG\_data data memeory space.

void fasp\_amg\_data\_bsr\_free (AMG\_data\_bsr \*mgl)

Free AMG\_data\_bsr data memeory space.

void fasp\_ilu\_data\_free (ILU\_data \*ILUdata)

Create ILU\_data sturcture.

void fasp\_ilu\_data\_null (ILU\_data \*ILUdata)

Initialize ILU data.

void fasp\_precond\_null (precond \*pcdata)

Initialize precond data.

## 9.39.1 Detailed Description

Initialize important data structures.

Note

Every structures should be initialized before usage.

Definition in file init.c.

#### 9.39.2 Function Documentation

9.39.2.1 AMG\_data\_bsr \* fasp\_amg\_data\_bsr\_create ( SHORT max\_levels )

Create and initialize AMG\_data data sturcture for AMG/SAMG (BSR format)

Parameters

max\_levels | Max number of levels allowed

Returns

Pointer to the AMG\_data data structure

**Author** 

Xiaozhe Hu

Date

08/07/2011

Definition at line 54 of file init.c.

9.39.2.2 void fasp\_amg\_data\_bsr\_free ( AMG\_data\_bsr \* mgl )

Free AMG\_data\_bsr data memeory space.

**Parameters** 

mgl Pointer to the AMG\_data\_bsr

**Author** 

Xiaozhe Hu

Date

2013/02/13

Definition at line 184 of file init.c.

9.39.2.3 AMG\_data \* fasp\_amg\_data\_create ( SHORT max\_levels )

Create and initialize AMG\_data for classical and SA AMG.

**Parameters** 

max_levels   Max number of levels allowed	
---	--

Returns

Pointer to the AMG\_data data structure

**Author** 

Chensong Zhang

Date

2010/04/06

Definition at line 27 of file init.c.

9.39.2.4 void fasp\_amg\_data\_free ( AMG\_data \* mgl, AMG\_param \* param )

Free AMG\_data data memeory space.

**Parameters** 

	mgl	Pointer to the AMG_data
Ì	param	Pointer to AMG parameters

Author

Chensong Zhang

9.39 init.c File Reference 173

Date

2010/04/06

Modified by Chensong Zhang on 05/05/2013: Clean up param as well!

Definition at line 137 of file init.c.

9.39.2.5 void fasp\_ilu\_data\_alloc ( INT iwk, INT nwork, ILU\_data \* iludata )

Allocate workspace for ILU factorization.

#### **Parameters**

iwk	Size of the index array
nwork	Size of the work array
iludata	Pointer to the ILU_data

## Author

Chensong Zhang

Date

2010/04/06

Definition at line 82 of file init.c.

9.39.2.6 void fasp\_ilu\_data\_free ( ILU\_data \* ILUdata )

Create ILU\_data sturcture.

**Parameters** 

ILUdata	Pointer to ILU_data
---------	---------------------

Author

Chensong Zhang

Date

2010/04/03

Definition at line 229 of file init.c.

9.39.2.7 void fasp\_ilu\_data\_null ( ILU\_data \* ILUdata )

Initialize ILU data.

#### **Parameters**

ILUdata Pointer to ILU\_data

**Author** 

Chensong Zhang

Date

2010/03/23

Definition at line 250 of file init.c.

9.39.2.8 void fasp\_precond\_null ( precond \* pcdata )

Initialize precond data.

**Parameters** 

pcdata | Pointer to precond

**Author** 

Chensong Zhang

Date

2010/03/23

Definition at line 266 of file init.c.

9.39.2.9 void fasp\_schwarz\_data\_free ( Schwarz\_data \* schwarz )

Free Schwarz\_data data memeory space.

**Parameters** 

\*schwarz | pointer to the AMG\_data data

**Author** 

Xiaozhe Hu

Date

2010/04/06

Definition at line 108 of file init.c.

# 9.40 input.c File Reference

Read input parameters.

```
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

void fasp\_param\_input (char \*filenm, input\_param \*Input)
 Read input parameters from disk file.

## 9.40.1 Detailed Description

Read input parameters.

Definition in file input.c.

#### 9.40.2 Function Documentation

```
9.40.2.1 void fasp_param_input ( char * filenm, input_param * Input )
```

Read input parameters from disk file.

#### **Parameters**

filenm	File name for input file
Input	Input parameters

#### **Author**

Chensong Zhang

Date

03/20/2010

Modified by Xiaozhe Hu on 01/23/2011: add AMLI cycle Modified by Chensong Zhang on 01/10/2012 Modified by Ludmil Zikatanov on 02/15/2013 Modified by Chensong Zhang on 05/10/2013: add a new input.

Definition at line 29 of file input.c.

# 9.41 interface mumps.c File Reference

Interface to MUMPS direct solvers.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

# **Functions**

- int fasp\_solver\_mumps (dCSRmat \*ptrA, dvector \*b, dvector \*u, const int print\_level)
   Solve Ax=b by MUMPS directly.
- int fasp\_solver\_mumps\_steps (dCSRmat \*ptrA, dvector \*b, dvector \*u, const int job)

  Solve Ax=b by MUMPS in three steps.

# 9.41.1 Detailed Description

Interface to MUMPS direct solvers.

Definition in file interface\_mumps.c.

#### 9.41.2 Function Documentation

9.41.2.1 int fasp\_solver\_mumps ( dCSRmat \* ptrA, dvector \* b, dvector \* u, const int print\_level )

Solve Ax=b by MUMPS directly.

#### **Parameters**

ptrA	Pointer to a dCSRmat matrix
b	Pointer to the dvector of right-hand side term
и	Pointer to the dvector of solution
print_level	Output level

#### **Author**

Chunsheng Feng

Date

02/27/2013

Modified by Chensong Zhang on 02/27/2013 for new FASP function names.

Definition at line 35 of file interface\_mumps.c.

9.41.2.2 int fasp\_solver\_mumps\_steps ( dCSRmat \* ptrA, dvector \* b, dvector \* u, const int job )

Solve Ax=b by MUMPS in three steps.

### **Parameters**

ptrA	Pointer to a dCSRmat matrix
b	Pointer to the dvector of right-hand side term
и	Pointer to the dvector of solution
job	1: Setup, 2: Sovle, 3 Destroy

#### **Author**

Chunsheng Feng

Date

02/27/2013

Modified by Chensong Zhang on 02/27/2013 for new FASP function names.

Definition at line 161 of file interface\_mumps.c.

# 9.42 interface\_samg.c File Reference

#### Interface to SAMG.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

void dvector2SAMGInput (dvector \*vec, char \*filename)

Write a dvector to disk file in SAMG format (coordinate format)

INT dCSRmat2SAMGInput (dCSRmat \*A, char \*filefrm, char \*fileamg)

Write SAMG Input data from a sparse matrix of CSR format.

# 9.42.1 Detailed Description

Interface to SAMG. Add reference for SAMG by K. Stuben here!

Definition in file interface\_samg.c.

#### 9.42.2 Function Documentation

9.42.2.1 INT dCSRmat2SAMGInput ( dCSRmat \* A, char \* filefrm, char \* fileamg )

Write SAMG Input data from a sparse matrix of CSR format.

### **Parameters**

*A	pointer to the dCSRmat matrix
*filefrm	pointer to the name of the .frm file
*fileamg	pointer to the name of the .amg file

### Author

Zhiyang Zhou

Date

2010/08/25

Definition at line 56 of file interface\_samg.c.

9.42.2.2 void dvector2SAMGInput ( dvector \* vec, char \* filename )

Write a dvector to disk file in SAMG format (coordinate format)

#### **Parameters**

* <i>Vec</i>	pointer to the dvector
*filename	char for vector file name

#### **Author**

Zhiyang Zhou

Date

08/25/2010

Definition at line 27 of file interface\_samg.c.

# 9.43 interface\_superlu.c File Reference

Interface to SuperLU direct solvers.

```
#include <stdio.h>
#include <stdlib.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

### **Functions**

• int fasp\_solver\_superlu (dCSRmat \*ptrA, dvector \*b, dvector \*u, const int print\_level)

Solve Au=b by SuperLU.

# 9.43.1 Detailed Description

Interface to SuperLU direct solvers.

Definition in file interface\_superlu.c.

#### 9.43.2 Function Documentation

9.43.2.1 int fasp\_solver\_superlu ( dCSRmat \* ptrA, dvector \* b, dvector \* u, const int print\_level )

Solve Au=b by SuperLU.

### **Parameters**

ptrA	Pointer to a dCSRmat matrix
b	Pointer to the dvector of right-hand side term

и	Pointer to the dvector of solution
print_level	Output level

#### Author

Xiaozhe Hu

Date

11/05/09

Modified by Chensong Zhang on 11/01/2012 for new FASP function names. Modified by Chensong Zhang on 02/27/2013 for new FASP function names.

Definition at line 39 of file interface superlu.c.

# 9.44 interface\_umfpack.c File Reference

Interface to UMFPACK direct solvers.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

### **Functions**

• int fasp\_solver\_umfpack (dCSRmat \*ptrA, dvector \*b, dvector \*u, const int print\_level) Solve Au=b by UMFpack.

## 9.44.1 Detailed Description

Interface to UMFPACK direct solvers.

Definition in file interface\_umfpack.c.

#### 9.44.2 Function Documentation

```
9.44.2.1 int fasp_solver_umfpack ( dCSRmat * ptrA, dvector * b, dvector * u, const int print_level )
```

Solve Au=b by UMFpack.

### **Parameters**

ptrA	Pointer to a dCSRmat matrix
b	Pointer to the dvector of right-hand side term
и	Pointer to the dvector of solution

print\_level Output level

**Author** 

Chensong Zhang

Date

05/20/2010

Modified by Chensong Zhang on 02/27/2013 for new FASP function names.

Definition at line 34 of file interface umfpack.c.

# 9.45 interpolation.c File Reference

Interpolation operators for AMG.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

- void fasp\_amg\_interp (dCSRmat \*A, ivector \*vertices, dCSRmat \*P, iCSRmat \*S, AMG\_param \*param)

  Generate interpolation operator P.
- void fasp\_amg\_interp1 (dCSRmat \*A, ivector \*vertices, dCSRmat \*P, AMG\_param \*param, iCSRmat \*S, INT \*icor\_ysk)

Generate interpolation operator P.

void fasp\_amg\_interp\_trunc (dCSRmat \*P, AMG\_param \*param)

Trunction step for prolongation operators.

# 9.45.1 Detailed Description

Interpolation operators for AMG.

Note

Ref U. Trottenberg, C. W. Oosterlee, and A. Schuller Multigrid (Appendix A: An Intro to Algebraic Multigrid) Academic Press Inc., San Diego, CA, 2001 With contributions by A. Brandt, P. Oswald and K. Stuben.

Definition in file interpolation.c.

#### 9.45.2 Function Documentation

9.45.2.1 void fasp\_amg\_interp ( dCSRmat \* A, ivector \* vertices, dCSRmat \* P, iCSRmat \* S, AMG\_param \* param )

Generate interpolation operator P.

## **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix (index starts from 0)
vertices	Indicator vector for the C/F splitting of the variables
Р	Prolongation (input: nonzero pattern, output: prolongation)
S	Strong connection matrix
param	AMG parameters

#### **Author**

Xuehai Huang, Chensong Zhang

Date

04/04/2010

Modified by Xiaozhe Hu on 05/23/2012: add S as input Modified by Chensong Zhang on 09/12/2012: clean up and debug interp RS Modified by Chensong Zhang on 05/14/2013: reconstruct the code

Definition at line 48 of file interpolation.c.

9.45.2.2 void fasp\_amg\_interp1 ( dCSRmat \* A, ivector \* vertices, dCSRmat \* P, AMG\_param \* param, iCSRmat \* S, INT \* icor\_ysk )

Generate interpolation operator P.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix (index starts from 0)
vertices	Indicator vector for the C/F splitting of the variables
Р	Prolongation (input: nonzero pattern, output: prolongation)
S	Strong connection matrix
param	AMG parameters
icor_ysk	Indices of coarse nodes in fine grid

### Returns

SUCCESS or error message

### Author

Chunsheng Feng, Xiaoqiang Yue

Date

03/01/2011

Modified by Chensong Zhang on 05/14/2013: reconstruct the code

Definition at line 105 of file interpolation.c.

9.45.2.3 void fasp\_amg\_interp\_trunc ( dCSRmat \* P,  $AMG_param * param$ )

Trunction step for prolongation operators.

#### **Parameters**

Р	Prolongation (input: full, output: truncated)
param	Pointer to AMG_param: AMG parameters

#### **Author**

Chensong Zhang

Date

05/14/2013

Originally by Xuehai Huang, Chensong Zhang on 01/31/2009 Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012: add OMP support Modified by Chensong Zhang on 05/14/2013: rewritten

Definition at line 158 of file interpolation.c.

# 9.46 interpolation\_em.c File Reference

Interpolation operators for AMG based on energy-min.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

void fasp\_amg\_interp\_em (dCSRmat \*A, ivector \*vertices, dCSRmat \*P, AMG\_param \*param)
 Energy-min interpolation.

## 9.46.1 Detailed Description

Interpolation operators for AMG based on energy-min.

Note

Ref J. Xu and L. Zikatanov "On An Energy Minimazing Basis in Algebraic Multigrid Methods" Computing and visualization in sciences, 2003

Definition in file interpolation\_em.c.

## 9.46.2 Function Documentation

9.46.2.1 void fasp\_amg\_interp\_em ( dCSRmat \* A, ivector \* vertices, dCSRmat \* P, AMG\_param \* param )

Energy-min interpolation.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix (index starts from 0)
vertices	Pointer to the indicator of CF splitting on fine or coarse grid
Р	Pointer to the dCSRmat matrix of resulted interpolation
param	Pointer to AMG_param: AMG parameters

#### **Author**

Shuo Zhang, Xuehai Huang

Date

04/04/2010

Modified by Chunsheng Feng, Zheng Li on 10/17/2012: add OMP support Modified by Chensong Zhang on 05/14/2013: reconstruct the code

Definition at line 49 of file interpolation em.c.

## 9.47 io.c File Reference

Matrix-vector input/output subroutines.

```
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

• void fasp\_dcsrvec1\_read (char \*filename, dCSRmat \*A, dvector \*b)

Read A and b from a SINGLE disk file.

void fasp\_dcsrvec2\_read (char \*filemat, char \*filerhs, dCSRmat \*A, dvector \*b)

Read A and b from two disk files.

void fasp\_dcsr\_read (char \*filename, dCSRmat \*A)

Read A from matrix disk file in IJ format.

void fasp\_dcoo\_read (char \*filename, dCSRmat \*A)

Read A from matrix disk file in IJ format – indices starting from 0.

• void fasp\_dcoo1\_read (char \*filename, dCOOmat \*A)

Read A from matrix disk file in IJ format – indices starting from 0.

void fasp\_dmtx\_read (char \*filename, dCSRmat \*A)

Read A from matrix disk file in MatrixMarket general format.

void fasp\_dmtxsym\_read (char \*filename, dCSRmat \*A)

Read A from matrix disk file in MatrixMarket sym format.

void fasp\_dstr\_read (char \*filename, dSTRmat \*A)

Read A from a disk file in dSTRmat format.

void fasp\_dbsr\_read (char \*filename, dBSRmat \*A)

Read A from a disk file in dBSRmat format.

void fasp dvecind read (char \*filename, dvector \*b)

Read b from matrix disk file.

void fasp\_dvec\_read (char \*filename, dvector \*b)

Read b from a disk file in array format.

void fasp\_ivecind\_read (char \*filename, ivector \*b)

Read b from matrix disk file.

void fasp\_ivec\_read (char \*filename, ivector \*b)

Read b from a disk file in array format.

void fasp\_dcsrvec1 write (char \*filename, dCSRmat \*A, dvector \*b)

Write A and b to a SINGLE disk file.

void fasp\_dcsrvec2\_write (char \*filemat, char \*filerhs, dCSRmat \*A, dvector \*b)

Write A and b to two disk files.

void fasp\_dcoo\_write (char \*filename, dCSRmat \*A)

Write a matrix to disk file in IJ format (coordinate format)

void fasp\_dstr\_write (char \*filename, dSTRmat \*A)

Write a dSTRmat to a disk file.

void fasp dbsr write (char \*filename, dBSRmat \*A)

Write a dBSRmat to a disk file.

void fasp\_dvec\_write (char \*filename, dvector \*vec)

Write a dvector to disk file.

void fasp\_dvecind\_write (char \*filename, dvector \*vec)

Write a dvector to disk file in coordinate format.

void fasp\_ivec\_write (char \*filename, ivector \*vec)

Write a ivector to disk file in coordinate format.

void fasp\_dvec\_print (INT n, dvector \*u)

Print first n entries of a vector of REAL type.

void fasp\_ivec\_print (INT n, ivector \*u)

Print first n entries of a vector of INT type.

void fasp\_dcsr\_print (dCSRmat \*A)

Print out a dCSRmat matrix in coordinate format.

void fasp\_dcoo\_print (dCOOmat \*A)

Print out a dCOOmat matrix in coordinate format.

void fasp\_dbsr\_print (dBSRmat \*A)

Print out a dBSRmat matrix in coordinate format.

void fasp\_dstr\_print (dSTRmat \*A)

Print out a dSTRmat matrix in coordinate format.

void fasp\_matrix\_read (char \*filename, void \*A)

Read matrix from different kinds of formats from both ASCII and binary files.

• void fasp\_matrix\_read\_bin (char \*filename, void \*A)

Read matrix in binary format.

void fasp\_matrix\_write (char \*filename, void \*A, INT flag)

write matrix from different kinds of formats from both ASCII and binary files

void fasp\_vector\_read (char \*filerhs, void \*b)

Read RHS vector from different kinds of formats from both ASCII and binary files.

void fasp\_vector\_write (char \*filerhs, void \*b, INT flag)

write RHS vector from different kinds of formats in both ASCII and binary files

## **Variables**

INT ilength

Flags which indicates lengths of INT and REAL numbers.

INT dlength

## 9.47.1 Detailed Description

Matrix-vector input/output subroutines.

Note

Read, write or print a matrix or a vector in various formats.

Definition in file io.c.

## 9.47.2 Function Documentation

9.47.2.1 void fasp\_dbsr\_print ( dBSRmat \* A )

Print out a dBSRmat matrix in coordinate format.

**Parameters** 

A	Pointer to the dBSRmat matrix A
---	---------------------------------

Author

Ziteng Wang

Date

12/24/2012

Definition at line 1381 of file io.c.

9.47.2.2 void fasp\_dbsr\_read ( char \* filename, dBSRmat \* A )

Read A from a disk file in dBSRmat format.

**Parameters** 

filename	File name for matrix A
Α	Pointer to the dBSRmat A

#### Note

This routine reads a dBSRmat matrix from a disk file in the following format: File format:

- · ROW, COL, NNZ
- · nb: size of each block
- storage\_manner: storage manner of each block

```
· ROW+1: length of IA
```

• IA(i), i=0:ROW

· NNZ: length of JA

• JA(i), i=0:NNZ-1

• NNZ\*nb\*nb: length of val

• val(i), i=0:NNZ\*nb\*nb-1

## **Author**

Xiaozhe Hu

Date

10/29/2010

Definition at line 635 of file io.c.

9.47.2.3 void fasp\_dbsr\_write ( char \* filename, dBSRmat \* A )

Write a dBSRmat to a disk file.

#### **Parameters**

filename	File name for A
Α	Pointer to the dBSRmat matrix A

## Note

The routine writes the specified REAL vector in BSR format. Refer to the reading subroutine  $\r$  fasp\_dbsr\_read.

#### **Author**

Shiquan Zhang

Date

10/29/2010

Definition at line 1143 of file io.c.

9.47.2.4 void fasp\_dcoo1\_read ( char \* filename, dCOOmat \* A )

Read A from matrix disk file in IJ format – indices starting from 0.

**Parameters** 

filename	File name for matrix
Α	Pointer to the COO matrix

#### Note

File format:

- nrow ncol nnz % number of rows, number of columns, and nnz
- i j a\_ij % i, j a\_ij in each line

difference between fasp\_dcoo\_read and this function is this function do not change to CSR format

**Author** 

Xiaozhe Hu

Date

03/24/2013

Definition at line 366 of file io.c.

9.47.2.5 void fasp\_dcoo\_print ( dCOOmat \* A )

Print out a dCOOmat matrix in coordinate format.

**Parameters** 

A Pointer to the dCOOmat matrix A

**Author** 

Ziteng Wang

Date

12/24/2012

Definition at line 1362 of file io.c.

9.47.2.6 void fasp\_dcoo\_read ( char \* filename, dCSRmat \* A )

Read A from matrix disk file in IJ format – indices starting from 0.

**Parameters** 

filename	File name for matrix
Α	Pointer to the CSR matrix

### Note

File format:

- nrow ncol nnz % number of rows, number of columns, and nnz
- i j a\_ij % i, j a\_ij in each line

After reading, it converts the matrix to dCSRmat format.

**Author** 

Xuehai Huang, Chensong Zhang

Date

03/29/2009

Definition at line 315 of file io.c.

9.47.2.7 void fasp\_dcoo\_write ( char \* filename, dCSRmat \* A )

Write a matrix to disk file in IJ format (coordinate format)

#### **Parameters**

Α	pointer to the dCSRmat matrix
filename	char for vector file name

#### Note

The routine writes the specified REAL vector in COO format. Refer to the reading subroutine \ref fasp\_dcoo\_read.

#### File format:

- The first line of the file gives the number of rows, the number of columns, and the number of nonzeros.
- Then gives nonzero values in i j a(i,j) format.

**Author** 

Chensong Zhang

Date

03/29/2009

Definition at line 1043 of file io.c.

9.47.2.8 void fasp\_dcsr\_print ( dCSRmat \* A )

Print out a dCSRmat matrix in coordinate format.

## **Parameters**

Α	Pointer to the dCSRmat matrix A

Author

Xuehai Huang

Date

03/29/2009

Definition at line 1340 of file io.c.

9.47.2.9 void fasp\_dcsr\_read ( char \* filename, dCSRmat \* A )

Read A from matrix disk file in IJ format.

## **Parameters**

*filename	char for matrix file name
* <i>A</i>	pointer to the CSR matrix

#### **Author**

Ziteng Wang

Date

12/25/2012

Definition at line 254 of file io.c.

9.47.2.10 void fasp\_dcsrvec1\_read ( char \* filename, dCSRmat \* A, dvector \* b )

Read A and b from a SINGLE disk file.

#### **Parameters**

filename	File name
Α	Pointer to the CSR matrix
b	Pointer to the dvector

#### Note

This routine reads a dCSRmat matrix and a dvector vector from a single disk file.

The difference between this and fasp\_dcoovec\_read is that this routine support non-square matrices.

## File format:

- nrow ncol % number of rows and number of columns
- ia(j), j=0:nrow % row index
- ja(j), j=0:nnz-1 % column index
- a(j), j=0:nnz-1 % entry value
- n % number of entries
- b(j), j=0:n-1 % entry value

## Author

Xuehai Huang

Date

03/29/2009

Modified by Chensong Zhang on 03/14/2012

Definition at line 84 of file io.c.

9.47.2.11 void fasp\_dcsrvec1\_write ( char \* filename, dCSRmat \* A, dvector \* b)

Write A and b to a SINGLE disk file.

## **Parameters**

filename	File name
Α	Pointer to the CSR matrix
b	Pointer to the dvector

#### Note

This routine writes a dCSRmat matrix and a dvector vector to a single disk file. File format:

- - ---
- nrow ncol % number of rows and number of columns
- ia(j), j=0:nrow % row index
- ja(j), j=0:nnz-1 % column index
- a(j), j=0:nnz-1 % entry value
- n % number of entries
- b(j), j=0:n-1 % entry value

#### **Author**

Feiteng Huang

Date

05/19/2012

Modified by Chensong on 12/26/2012

Definition at line 895 of file io.c.

9.47.2.12 void fasp\_dcsrvec2\_read ( char \* filemat, char \* filerhs, dCSRmat \* A, dvector \* b )

Read A and b from two disk files.

#### **Parameters**

filemat	File name for matrix
filerhs	File name for right-hand side
Α	Pointer to the dCSR matrix
b	Pointer to the dvector

## Note

This routine reads a dCSRmat matrix and a dvector vector from a disk file.

## CSR matrix file format:

- nrow % number of columns (rows)
- ia(j), j=0:nrow % row index
- ja(j), j=0:nnz-1 % column index
- a(j), j=0:nnz-1 % entry value

## RHS file format:

- n % number of entries
- b(j), j=0:nrow-1 % entry value

Indices start from 1, NOT 0!!!

**Author** 

Zhiyang Zhou

Date

2010/08/06

Modified by Chensong Zhang on 2011/03/01 Modified by Chensong Zhang on 2012/01/05 Definition at line 175 of file io.c.

9.47.2.13 void fasp\_dcsrvec2\_write ( char \* filemat, char \* filerhs, dCSRmat \* A, dvector \* b )

Write A and b to two disk files.

#### **Parameters**

filemat	File name for matrix
filerhs	File name for right-hand side
Α	Pointer to the dCSR matrix
b	Pointer to the dvector

#### Note

This routine writes a dCSRmat matrix and a dvector vector to two disk files.

## CSR matrix file format:

- nrow % number of columns (rows)
- ia(j), j=0:nrow % row index
- ja(j), j=0:nnz-1 % column index
- a(j), j=0:nnz-1 % entry value

## RHS file format:

- n % number of entries
- b(j), j=0:nrow-1 % entry value

Indices start from 1, NOT 0!!!

**Author** 

Feiteng Huang

Date

05/19/2012

Definition at line 972 of file io.c.

9.47.2.14 void fasp\_dmtx\_read ( char \* filename, dCSRmat \* A )

Read A from matrix disk file in MatrixMarket general format.

## **Parameters**

file	ename	File name for matrix
	Α	Pointer to the CSR matrix

#### Note

File format: This routine reads a MatrixMarket general matrix from a mtx file. And it converts the matrix to dCS-Rmat format. For details of mtx format, please refer to http://math.nist.gov/MatrixMarket/. Indices start from 1, NOT 0!!!

**Author** 

Chensong Zhang

Date

09/05/2011

Definition at line 416 of file io.c.

9.47.2.15 void fasp\_dmtxsym\_read ( char \* filename, dCSRmat \* A )

Read A from matrix disk file in MatrixMarket sym format.

#### **Parameters**

filename	File name for matrix
Α	Pointer to the CSR matrix

## Note

File format: This routine reads a MatrixMarket symmetric matrix from a mtx file. And it converts the matrix to dCSRmat format. For details of mtx format, please refer to http://math.nist.gov/MatrixMarket/.

```
Indices start from 1, NOT 0!!!
```

Author

Chensong Zhang

Date

09/02/2011

Definition at line 478 of file io.c.

9.47.2.16 void fasp\_dstr\_print ( dSTRmat \* A )

Print out a dSTRmat matrix in coordinate format.

## **Parameters**

Α	Pointer to the dSTRmat matrix A
---	---------------------------------

**Author** 

Ziteng Wang

Date

12/24/2012

Definition at line 1408 of file io.c.

9.47.2.17 void fasp\_dstr\_read ( char \* filename, dSTRmat \* A )

Read A from a disk file in dSTRmat format.

## **Parameters**

filename	File name for the matrix
Α	Pointer to the dSTRmat

#### Note

This routine reads a dSTRmat matrix from a disk file. After done, it converts the matrix to dCSRmat format. File format:

- nx, ny, nz
- · nc: number of components
- · nband: number of bands
- n: size of diagonal, you must have diagonal
- diag(j), j=0:n-1
- · offset, length: offset and length of off-diag1
- offdiag(j), j=0:length-1

**Author** 

Xuehai Huang

Date

03/29/2009

Definition at line 555 of file io.c.

9.47.2.18 void fasp\_dstr\_write ( char \* filename, dSTRmat \* A )

Write a dSTRmat to a disk file.

## **Parameters**

ſ	filename	File name for A
	Α	Pointer to the dSTRmat matrix A

#### Note

The routine writes the specified REAL vector in STR format. Refer to the reading subroutine  $\r$  fasp\_dstr\_read.

**Author** 

Shiquan Zhang

Date

03/29/2010

Definition at line 1083 of file io.c.

9.47.2.19 void fasp\_dvec\_print (INT n, dvector \* u)

Print first n entries of a vector of REAL type.

#### **Parameters**

n	An interger (if n=0, then print all entries)
и	Pointer to a dvector

#### **Author**

Chensong Zhang

Date

03/29/2009

Definition at line 1301 of file io.c.

9.47.2.20 void fasp\_dvec\_read ( char \* filename, dvector \* b )

Read b from a disk file in array format.

### **Parameters**

ſ	filename	File name for vector b
	b	Pointer to the dvector b (output)

## Note

File Format:

- nrow
- val\_j, j=0:nrow-1

**Author** 

Chensong Zhang

Date

03/29/2009

Definition at line 754 of file io.c.

9.47.2.21 void fasp\_dvec\_write ( char \* filename, dvector \* vec )

Write a dvector to disk file.

#### **Parameters**

vec	Pointer to the dvector
filename	File name

**Author** 

Xuehai Huang

Date

03/29/2009

Definition at line 1198 of file io.c.

9.47.2.22 void fasp\_dvecind\_read ( char \* filename, dvector \* b )

Read b from matrix disk file.

**Parameters** 

filename	File name for vector b
b	Pointer to the dvector b (output)

Note

File Format:

- nrow
- ind\_j, val\_j, j=0:nrow-1

Because the index is given, order is not important!

Author

Chensong Zhang

Date

03/29/2009

Definition at line 704 of file io.c.

9.47.2.23 void fasp\_dvecind\_write ( char \* filename, dvector \* vec )

Write a dvector to disk file in coordinate format.

## **Parameters**

vec	Pointer to the dvector
filename	File name

#### Note

The routine writes the specified REAL vector in IJ format.

- The first line of the file is the length of the vector;
- · After that, each line gives index and value of the entries.

## **Author**

Xuehai Huang

Date

03/29/2009

Definition at line 1234 of file io.c.

9.47.2.24 void fasp\_ivec\_print ( INT n, ivector \*u )

Print first n entries of a vector of INT type.

#### **Parameters**

n	An interger (if n=0, then print all entries)
и	Pointer to an ivector

## **Author**

Chensong Zhang

Date

03/29/2009

Definition at line 1321 of file io.c.

9.47.2.25 void fasp\_ivec\_read ( char \* filename, ivector \* b )

Read b from a disk file in array format.

## **Parameters**

filename	File name for vector b
b	Pointer to the dvector b (output)

Note

File Format:

- nrow
- val\_j, j=0:nrow-1

**Author** 

Xuehai Huang

Date

03/29/2009

Definition at line 844 of file io.c.

9.47.2.26 void fasp\_ivec\_write ( char \* filename, ivector \* vec )

Write a ivector to disk file in coordinate format.

## **Parameters**

vec	Pointer to the dvector
filename	File name

#### Note

The routine writes the specified INT vector in IJ format.

- The first line of the file is the length of the vector;
- · After that, each line gives index and value of the entries.

**Author** 

Xuehai Huang

Date

03/29/2009

Definition at line 1269 of file io.c.

9.47.2.27 void fasp\_ivecind\_read ( char \* filename, ivector \* b )

Read b from matrix disk file.

**Parameters** 

filename	File name for vector b

## b Pointer to the dvector b (output)

Note

File Format:

- nrow
- ind\_j, val\_j ... j=0:nrow-1

**Author** 

Chensong Zhang

Date

03/29/2009

Definition at line 804 of file io.c.

9.47.2.28 fasp\_matrix\_read ( char \* filemat, void \* A )

Read matrix from different kinds of formats from both ASCII and binary files.

#### **Parameters**

filemat	File name of matrix file
Α	Pointer to the matrix

#### Note

Flags for matrix file format:

- fileflag % fileflag = 1: binary, fileflag = 0000: ASCII
- formatflag % a 3-digit number for internal use, see below
- · matrix % different types of matrix

Meaning of formatflag:

- · matrixflag % first digit of formatflag
  - matrixflag = 1: CSR format
  - matrixflag = 2: BSR format
  - matrixflag = 3: STR format
  - matrixflag = 4: COO format
  - matrixflag = 5: MTX format
  - matrixflag = 6: MTX symmetrical format
- ilength % third digit of formatflag, length of INT
- · dlength % fourth digit of formatflag, length of REAL

**Author** 

Ziteng Wang

Date

12/24/2012

Modified by Chensong Zhang on 05/01/2013

Definition at line 1442 of file io.c.

9.47.2.29 void fasp\_matrix\_read\_bin ( char \* filemat, void \* A )

Read matrix in binary format.

#### **Parameters**

filemat	File name of matrix file
Α	Pointer to the matrix

## **Author**

Xiaozhe Hu

Date

04/14/2013

Modified by Chensong Zhang on 05/01/2013: Use it to read binary files!!!

Definition at line 1547 of file io.c.

9.47.2.30 fasp\_matrix\_write ( char \* filemat, void \* A, INT flag )

write matrix from different kinds of formats from both ASCII and binary files

#### **Parameters**

filemat	File name of matrix file
Α	Pointer to the matrix
flag	Type of file and matrix, a 3-digit number

## Note

Meaning of flag:

- fileflag % fileflag = 1: binary, fileflag = 0: ASCII
- matrixflag
  - matrixflag = 1: CSR format
  - matrixflag = 2: BSR format
  - matrixflag = 3: STR format

Matrix file format:

- fileflag % fileflag = 1: binary, fileflag = 0000: ASCII
- formatflag % a 3-digit number
- · matrixflag % different kinds of matrix judged by formatflag

Author

Ziteng Wang

Date

12/24/2012

Definition at line 1621 of file io.c.

9.47.2.31 fasp\_vector\_read ( char \* filerhs, void \* b )

Read RHS vector from different kinds of formats from both ASCII and binary files.

## **Parameters**

filerhs	File name of vector file
b	Pointer to the vector

#### Note

Matrix file format:

- fileflag % fileflag = 1: binary, fileflag = 0000: ASCII
- formatflag % a 3-digit number
- · vector % different kinds of vector judged by formatflag

Meaning of formatflag:

- · vectorflag % first digit of formatflag
  - vectorflag = 1: dvec format
  - vectorflag = 2: ivec format
  - vectorflag = 3: dvecind format
  - vectorflag = 4: ivecind format
- ilength % second digit of formatflag, length of INT
- · dlength % third digit of formatflag, length of REAL

#### **Author**

Ziteng Wang

## Date

12/24/2012

Definition at line 1714 of file io.c.

9.47.2.32 fasp\_vector\_write ( char \* filerhs, void \* b, INT flag )

write RHS vector from different kinds of formats in both ASCII and binary files

#### **Parameters**

	filerhs	File name of vector file
Ī	b	Pointer to the vector
	flag	Type of file and vector, a 2-digit number

## Note

Meaning of the flags

- fileflag % fileflag = 1: binary, fileflag = 0: ASCII
- · vectorflag
  - vectorflag = 1: dvec format
  - vectorflag = 2: ivec format
  - vectorflag = 3: dvecind format
  - vectorflag = 4: ivecind format

Matrix file format:

- fileflag % fileflag = 1: binary, fileflag = 0000: ASCII
- · formatflag % a 2-digit number
- · vectorflag % different kinds of vector judged by formatflag

**Author** 

Ziteng Wang

Date

12/24/2012

Modified by Chensong Zhang on 05/02/2013: fix a bug when writing in binary format Definition at line 1811 of file io.c.

# 9.48 itsolver\_bcsr.c File Reference

Iterative solvers for block\_dCSRmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_block.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

#### **Functions**

• INT fasp\_solver\_bdcsr\_itsolver (block\_dCSRmat \*A, dvector \*b, dvector \*x, precond \*pc, itsolver\_param \*itparam)

```
Solve Ax = b by standard Krylov methods.
```

• INT fasp\_solver\_bdcsr\_krylov (block\_dCSRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam)

Solve Ax = b by standard Krylov methods.

## 9.48.1 Detailed Description

Iterative solvers for block\_dCSRmat matrices.

Definition in file itsolver\_bcsr.c.

## 9.48.2 Function Documentation

9.48.2.1 INT fasp\_solver\_bdcsr\_itsolver ( block\_dCSRmat \* A, dvector \* b, dvector \* x, precond \* pc, itsolver\_param \* itparam )

Solve Ax = b by standard Krylov methods.

## **Parameters**

Α	Pointer to the coeff matrix in block_dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
рс	Pointer to the preconditioning action
itparam	Pointer to parameters for iterative solvers

#### Returns

Number of iterations if succeed

## **Author**

Chensong Zhang

Date

11/25/2010

Definition at line 35 of file itsolver\_bcsr.c.

9.48.2.2 INT fasp\_solver\_bdcsr\_krylov ( block\_dCSRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam )

Solve Ax = b by standard Krylov methods.

#### **Parameters**

Α	Pointer to the coeff matrix in block_dCSRmat format
b	Pointer to the right hand side in dvector format
Х	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

## Returns

Number of iterations if succeed

## **Author**

Xiaozhe Hu

Date

07/18/2010

Definition at line 105 of file itsolver\_bcsr.c.

# 9.49 itsolver\_bsr.c File Reference

Iterative solvers for dBSRmat matrices.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

## **Functions**

· void fasp set GS threads (INT mythreads, INT its)

Set threads for CPR. Please add it at the begin of Krylov openmp method function and after iter++.

• INT fasp\_solver\_dbsr\_itsolver (dBSRmat \*A, dvector \*b, dvector \*x, precond \*pc, itsolver\_param \*itparam)

Solve Ax=b by preconditioned Krylov methods for BSR matrices.

INT fasp\_solver\_dbsr\_krylov (dBSRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam)

Solve Ax=b by standard Krylov methods for BSR matrices.

• INT fasp\_solver\_dbsr\_krylov\_diag (dBSRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam)

Solve Ax=b by diagonal preconditioned Krylov methods.

• INT fasp\_solver\_dbsr\_krylov\_ilu (dBSRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam, ILU\_param \*iluparam)

Solve Ax=b by ILUs preconditioned Krylov methods.

• INT fasp\_solver\_dbsr\_krylov\_amg (dBSRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam, AMG\_param \*amgparam)

Solve Ax=b by AMG preconditioned Krylov methods.

#### **Variables**

- INT THDs AMG GS =0
- INT THDs CPR IGS =0
- INT THDs CPR gGS =0

## 9.49.1 Detailed Description

Iterative solvers for dBSRmat matrices.

Definition in file itsolver\_bsr.c.

## 9.49.2 Function Documentation

9.49.2.1 void fasp\_set\_GS\_threads ( INT threads, INT its )

Set threads for CPR. Please add it at the begin of Krylov openmp method function and after iter++.

## **Parameters**

threads	Total threads of sovler
its	Current its of the Krylov methods

#### Author

Feng Chunsheng, Yue Xiaoqiang

Date

03/20/2011

TODO: Why put it here??? -Chensong

Definition at line 39 of file itsolver bsr.c.

9.49.2.2 INT fasp\_solver\_dbsr\_itsolver ( dBSRmat \* A, dvector \* b, dvector \* x, precond \* pc, itsolver\_param \* itparam )

Solve Ax=b by preconditioned Krylov methods for BSR matrices.

## **Parameters**

Α	Pointer to the coeff matrix in dBSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
рс	Pointer to the preconditioning action
itparam	Pointer to parameters for iterative solvers

## Returns

Number of iterations if succeed

## **Author**

Zhiyang Zhou, Xiaozhe Hu

Date

10/26/2010

Definition at line 100 of file itsolver\_bsr.c.

9.49.2.3 INT fasp\_solver\_dbsr\_krylov ( dBSRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam )

Solve Ax=b by standard Krylov methods for BSR matrices.

## **Parameters**

Α	Pointer to the coeff matrix in dBSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

## Returns

Number of iterations if succeed

## **Author**

Zhiyang Zhou, Xiaozhe Hu

Date

10/26/2010

Definition at line 175 of file itsolver\_bsr.c.

9.49.2.4 INT fasp\_solver\_dbsr\_krylov\_amg ( dBSRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam, AMG\_param \* amgparam )

Solve Ax=b by AMG preconditioned Krylov methods.

## **Parameters**

Α	Pointer to the coeff matrix in dBSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
amgparam	Pointer to parameters of AMG

## Returns

Number of iterations if succeed

Author

Xiaozhe Hu

Date

03/16/2012

parameters of iterative method

Definition at line 382 of file itsolver\_bsr.c.

9.49.2.5 INT fasp\_solver\_dbsr\_krylov\_diag ( dBSRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam )

Solve Ax=b by diagonal preconditioned Krylov methods.

## **Parameters**

Α	Pointer to the coeff matrix in dBSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

## Returns

the number of iterations

**Author** 

Zhiyang Zhou, Xiaozhe Hu

Date

10/26/2010

Modified by Chunsheng Feng, Zheng Li

Date

10/15/2012

Definition at line 219 of file itsolver\_bsr.c.

9.49.2.6 INT fasp\_solver\_dbsr\_krylov\_ilu ( dBSRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam, ILU\_param \* iluparam )

Solve Ax=b by ILUs preconditioned Krylov methods.

## **Parameters**

Α	Pointer to the coeff matrix in dBSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
iluparam	Pointer to parameters of ILU

## Returns

Number of iterations if succeed

## **Author**

Shiquang Zhang, Xiaozhe Hu

#### Date

10/26/2010

Definition at line 315 of file itsolver\_bsr.c.

## 9.49.3 Variable Documentation

9.49.3.1 INT THDs\_AMG\_GS =0

cpr amg gs smoothing threads

Definition at line 35 of file itsolver\_bsr.c.

```
9.49.3.2 INT THDs_CPR_gGS =0
```

global matrix gs smoothing threads

Definition at line 37 of file itsolver\_bsr.c.

```
9.49.3.3 INT THDs_CPR_IGS =0
```

reservoir gs smoothing threads

Definition at line 36 of file itsolver\_bsr.c.

# 9.50 itsolver\_csr.c File Reference

Iterative solvers for dCSRmat matrices.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

#### **Functions**

• INT fasp\_solver\_dcsr\_itsolver (dCSRmat \*A, dvector \*b, dvector \*x, precond \*pc, itsolver\_param \*itparam)

Solve Ax=b by preconditioned Krylov methods for CSR matrices.

INT fasp\_solver\_dcsr\_krylov (dCSRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam)

Solve Ax=b by standard Krylov methods for CSR matrices.

INT fasp\_solver\_dcsr\_krylov\_diag (dCSRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam)

Solve Ax=b by diagonal preconditioned Krylov methods.

 INT fasp\_solver\_dcsr\_krylov\_schwarz (dCSRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam, Schwarz-\_param \*schparam)

Solve Ax=b by overlapping schwarz Krylov methods.

INT fasp\_solver\_dcsr\_krylov\_amg (dCSRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam, AMG\_param \*amgparam)

Solve Ax=b by AMG preconditioned Krylov methods.

• INT fasp\_solver\_dcsr\_krylov\_ilu (dCSRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam, ILU\_param \*iluparam)

Solve Ax=b by ILUs preconditioned Krylov methods.

• INT fasp\_solver\_dcsr\_krylov\_ilu\_M (dCSRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam, ILU\_param \*iluparam, dCSRmat \*M)

Solve Ax=b by ILUs preconditioned Krylov methods: ILU of M as preconditioner.

## 9.50.1 Detailed Description

Iterative solvers for dCSRmat matrices.

Definition in file itsolver csr.c.

### 9.50.2 Function Documentation

9.50.2.1 INT fasp\_solver\_dcsr\_itsolver ( dCSRmat \* A, dvector \* b, dvector \* x, precond \* pc, itsolver\_param \* itparam )

Solve Ax=b by preconditioned Krylov methods for CSR matrices.

#### **Parameters**

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
рс	Pointer to the preconditioning action
itparam	Pointer to parameters for iterative solvers

#### Returns

Number of iterations if succeed

## Author

Chensong Zhang

Date

09/25/2009

Note

This is an abstract interface for iterative methods.

Definition at line 39 of file itsolver\_csr.c.

9.50.2.2 INT fasp\_solver\_dcsr\_krylov ( dCSRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam )

Solve Ax=b by standard Krylov methods for CSR matrices.

#### **Parameters**

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

#### Returns

Number of iterations if succeed

## Author

Chensong Zhang, Shiquan Zhang

Date

09/25/2009

Definition at line 139 of file itsolver csr.c.

9.50.2.3 INT fasp\_solver\_dcsr\_krylov\_amg ( dCSRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam, AMG\_param \* amgparam )

Solve Ax=b by AMG preconditioned Krylov methods.

## **Parameters**

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
amgparam	Pointer to parameters for AMG methods

#### Returns

Number of iterations if succeed

**Author** 

Chensong Zhang

Date

09/25/2009

Definition at line 330 of file itsolver\_csr.c.

9.50.2.4 INT fasp\_solver\_dcsr\_krylov\_diag ( dCSRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam )

Solve Ax=b by diagonal preconditioned Krylov methods.

#### **Parameters**

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
Х	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

#### Returns

Number of iterations if succeed

## **Author**

Chensong Zhang, Shiquan Zhang

Date

09/25/2009

Definition at line 189 of file itsolver\_csr.c.

9.50.2.5 INT fasp\_solver\_dcsr\_krylov\_ilu ( dCSRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam, ILU\_param \* iluparam )

Solve Ax=b by ILUs preconditioned Krylov methods.

## **Parameters**

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
iluparam	Pointer to parameters for ILU

#### Returns

Number of iterations if succeed

**Author** 

Chensong Zhang, Shiquan Zhang

Date

09/25/2009

Definition at line 438 of file itsolver\_csr.c.

9.50.2.6 INT fasp\_solver\_dcsr\_krylov\_ilu\_M ( dCSRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam, ILU\_param \* iluparam, dCSRmat \* M )

Solve Ax=b by ILUs preconditioned Krylov methods: ILU of M as preconditioner.

#### **Parameters**

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
iluparam	Pointer to parameters for ILU
М	Pointer to the preconditioning matrix in dCSRmat format

## Returns

Number of iterations if succeed

Author

Xiaozhe Hu

Date

09/25/2009

Note

This function is specially designed for reservoir simulation. Have not been tested in any other places.

Definition at line 525 of file itsolver\_csr.c.

9.50.2.7 INT fasp\_solver\_dcsr\_krylov\_schwarz ( dCSRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam, Schwarz\_param \* schparam )

Solve Ax=b by overlapping schwarz Krylov methods.

**Parameters** 

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
schparam	Pointer to parameters for Schwarz methods

#### Returns

Number of iterations

**Author** 

Xiaozhe Hu

Date

03/21/2011

Modified by Chensong on 07/02/2012: change interface

Definition at line 253 of file itsolver\_csr.c.

## 9.51 itsolver\_mf.c File Reference

Iterative solvers with matrix-free spmv.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "fasp_block.h"
#include "itsolver_util.inl"
```

## **Functions**

- INT fasp\_solver\_itsolver (mxv\_matfree \*mf, dvector \*b, dvector \*x, precond \*pc, itsolver\_param \*itparam)

  Solve Ax=b by preconditioned Krylov methods for CSR matrices.
- INT fasp\_solver\_krylov (mxv\_matfree \*mf, dvector \*b, dvector \*x, itsolver\_param \*itparam)

Solve Ax=b by standard Krylov methods – without preconditioner.

void fasp\_solver\_itsolver\_init (INT matrix\_format, mxv\_matfree \*mf, void \*A)
 Initialize itsovlers.

## 9.51.1 Detailed Description

Iterative solvers with matrix-free spmv.

Definition in file itsolver\_mf.c.

# 9.51.2 Function Documentation

9.51.2.1 INT fasp\_solver\_itsolver ( mxv\_matfree \* mf, dvector \* b, dvector \* x, precond \* pc, itsolver\_param \* itparam )

Solve Ax=b by preconditioned Krylov methods for CSR matrices.

#### **Parameters**

mf	Pointer to mxv_matfree matrix-free spmv operation
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
рс	Pointer to the preconditioning action
itparam	Pointer to parameters for iterative solvers

# Returns

Number of iterations if succeed

#### **Author**

Chensong Zhang

Date

09/25/2009

Note

This is an abstract interface for iterative methods.

Modified by Feiteng Huang on 09/19/2012: matrix free

Definition at line 50 of file itsolver\_mf.c.

9.51.2.2 void fasp\_solver\_itsolver\_init ( INT matrix\_format, mxv\_matfree \* mf, void \* A )

Initialize itsovlers.

#### **Parameters**

matrix_format	matrix format
mf	Pointer to mxv_matfree matrix-free spmv operation
Α	void pointer to matrix

#### **Author**

Feiteng Huang

Date

09/18/2012

Modified by Chensong Zhang on 05/10/2013: Change interface of mat-free mv Definition at line 199 of file itsolver\_mf.c.

9.51.2.3 INT fasp\_solver\_krylov (  $mxv_matfree * mf$ , dvector \* b, dvector \* x,  $itsolver_param * itparam$  )

Solve Ax=b by standard Krylov methods – without preconditioner.

#### **Parameters**

mf	Pointer to mxv_matfree matrix-free spmv operation
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

#### Returns

Number of iterations if succeed

#### **Author**

Chensong Zhang, Shiquan Zhang

Date

09/25/2009

Modified by Feiteng Huang on 09/20/2012: matrix free

Definition at line 151 of file itsolver\_mf.c.

# 9.52 itsolver str.c File Reference

Iterative solvers for dSTRmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver util.inl"
```

# **Functions**

- INT fasp\_solver\_dstr\_itsolver (dSTRmat \*A, dvector \*b, dvector \*x, precond \*pc, itsolver\_param \*itparam)

  Solve Ax=b by standard Krylov methods.
- INT fasp\_solver\_dstr\_krylov (dSTRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam)

Solve Ax=b by standard Krylov methods.

- INT fasp\_solver\_dstr\_krylov\_diag (dSTRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam)
- INT fasp\_solver\_dstr\_krylov\_ilu (dSTRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam, ILU\_param \*iluparam)

Solve Ax=b by structured ILU preconditioned Krylov methods.

Solve Ax=b by diagonal preconditioned Krylov methods.

• INT fasp\_solver\_dstr\_krylov\_blockgs (dSTRmat \*A, dvector \*b, dvector \*x, itsolver\_param \*itparam, ivector \*neigh, ivector \*order)

Solve Ax=b by diagonal preconditioned Krylov methods.

# 9.52.1 Detailed Description

Iterative solvers for dSTRmat matrices.

Definition in file itsolver\_str.c.

# 9.52.2 Function Documentation

9.52.2.1 INT fasp\_solver\_dstr\_itsolver ( dSTRmat \* A, dvector \* b, dvector \* x, precond \* pc, itsolver\_param \* itparam )

Solve Ax=b by standard Krylov methods.

#### **Parameters**

Α	Pointer to the coeff matrix in dSTRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
рс	Pointer to the preconditioning action
itparam	Pointer to parameters for iterative solvers

#### Returns

Number of iterations if succeed

#### **Author**

Chensong Zhang

#### Date

09/25/2009

Definition at line 34 of file itsolver\_str.c.

9.52.2.2 INT fasp\_solver\_dstr\_krylov ( dSTRmat \* A, dvector \* b, dvector \* x,  $itsolver_param * itparam$  )

Solve Ax=b by standard Krylov methods.

#### **Parameters**

Α	Pointer to the coeff matrix in dSTRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

# Returns

Number of iterations if succeed

# Author

Zhiyang Zhou

Date

04/25/2010

Definition at line 109 of file itsolver\_str.c.

9.52.2.3 INT fasp\_solver\_dstr\_krylov\_blockgs ( dSTRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam, ivector \* neigh, ivector \* order )

Solve Ax=b by diagonal preconditioned Krylov methods.

#### **Parameters**

Α	Pointer to the coeff matrix in dSTRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
neigh	Pointer to neighbor vector
order	Pointer to solver ordering

### Returns

Number of iterations if succeed

**Author** 

Xiaozhe Hu

Date

10/10/2010

Definition at line 290 of file itsolver\_str.c.

9.52.2.4 INT fasp\_solver\_dstr\_krylov\_diag ( dSTRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam )

Solve Ax=b by diagonal preconditioned Krylov methods.

### **Parameters**

Α	Pointer to the coeff matrix in dSTRmat format
b	Pointer to the right hand side in dvector format
Χ	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

#### Returns

Number of iterations if succeed

Author

Zhiyang Zhou

Date

4/23/2010

Definition at line 149 of file itsolver\_str.c.

9.52.2.5 INT fasp\_solver\_dstr\_krylov\_ilu ( dSTRmat \* A, dvector \* b, dvector \* x, itsolver\_param \* itparam, ILU param \* iluparam )

Solve Ax=b by structured ILU preconditioned Krylov methods.

#### **Parameters**

Α	Pointer to the coeff matrix in dSTRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
iluparam	Pointer to parameters for ILU

#### Returns

Number of iterations if succeed

#### **Author**

Xiaozhe Hu

Date

05/01/2010

Definition at line 207 of file itsolver\_str.c.

# 9.53 itsolver util.inl File Reference

Routines for iterative solvers.

### **Macros**

- #define ITS\_FACONV printf("### WARNING: False convergence!\n")
   Warning for residual false convergence.
- #define ITS\_ZEROSOL printf("### WARNING: Iteration stopped due to the solution is close to zero!\n")
   Warning for solution close to zero.
- #define ITS\_RESTART printf("### WARNING: Iteration restarted due to stagnation!\n")

Warning for iteration restarted.

 $\bullet \ \ \text{\#define ITS\_STAGGED printf("\#\#\# WARNING: Iteration stopped due to staggnation! \verb|\n"|)}$ 

Warning for stagged iteration.

- #define ITS\_ZEROTOL printf("### WARNING: The tolerence might be too small!\n")
- Warning for tolerance practically close to zero.

   #define ITS DIVZERO printf("### WARNING: Divided by zero!\n")

Warning for divided by zero.

- #define ITS\_REALRES(relres) printf("### WARNING: The actual relative residual = %e!\n",(relres)) Warning for actual relative residual.
- #define ITS\_COMPRES(relres) printf("### WARNING: The computed relative residual = %e!\n",(relres))
   Warning for computed relative residual.

#define ITS\_SMALLSP printf("### WARNING: The sp is too small!\n")
 Warning for too small sp.

• #define ITS\_RESTORE(iter) printf("### WARNING: Restore iteration %d!!!",(iter));

Warning for restore previous iteration.

Output L2 norm of some variable.

- #define ITS\_DIFFRES(reldiff, relres) printf("||u-u'|| = %e and the comp. rel. res. = %e.\n",(reldiff),(relres));

  Output relative difference and residual.
- #define ITS\_PUTNORM(name, value) printf("L2 norm of %s = %e.\n",(name),(value));

# 9.53.1 Detailed Description

Routines for iterative solvers.

Definition in file itsolver\_util.inl.

# 9.54 linklist.inl File Reference

Utilies for link list data structure.

#### **Macros**

- #define LIST\_HEAD -1
- #define LIST\_TAIL -2

# 9.54.1 Detailed Description

Utilies for link list data structure.

Note

These linked-list operations are adapted from hypre 2.0

Definition in file linklist.inl.

#### 9.54.2 Macro Definition Documentation

9.54.2.1 #define LIST\_HEAD -1

head of the linked list

Definition at line 7 of file linklist.inl.

9.54.2.2 #define LIST\_TAIL -2

tail of the linked list

Definition at line 8 of file linklist.inl.

# 9.55 lu.c File Reference

LU decomposition and direct solve for dense matrix.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

• SHORT fasp\_smat\_lu\_decomp (REAL \*A, INT pivot[], INT n)

LU decomposition of A usind Doolittle's method.

SHORT fasp\_smat\_lu\_solve (REAL \*A, REAL b[], INT pivot[], REAL x[], INT n)

Solving Ax=b using LU decomposition.

### 9.55.1 Detailed Description

LU decomposition and direct solve for dense matrix.

Definition in file lu.c.

#### 9.55.2 Function Documentation

```
9.55.2.1 SHORT fasp_smat_lu_decomp ( REAL * A, INT pivot[], INT n )
```

LU decomposition of A usind Doolittle's method.

#### **Parameters**

Α	Pointer to the full matrix
pivot	Pivoting positions
n	Size of matrix A

### Returns

SUCCESS if succeed, RUN FAIL if fail

#### Note

Use Doolittle's method to decompose the n x n matrix A into a unit lower triangular matrix L and an upper triangular matrix U such that A = LU. The matrices L and U replace the matrix A. The diagonal elements of L are 1 and are not stored.

The Doolittle method with partial pivoting is: Determine the pivot row and interchange the current row with the pivot row, then assuming that row k is the current row, k = 0, ..., n - 1 evaluate in order the following pair of expressions U[k][j] = A[k][j] - (L[k][0]\*U[0][j] + ... + L[k][k-1]\*U[k-1][j]) for j = k, k+1, ..., n-1 L[i][k] = (A[i][k] - (L[i][0]\*U[0][k] + ... + L[i][k-1]\*U[k-1][k])) / U[k][k] for i = k+1, ..., n-1.

#### **Author**

Xuehai Huang

Date

04/02/2009

Definition at line 46 of file lu.c.

9.55.2.2 SHORT fasp\_smat\_lu\_solve ( REAL \* A, REAL b[], INT pivot[], REAL x[], INT n )

Solving Ax=b using LU decomposition.

#### **Parameters**

Α	Pointer to the full matrix
b	Right hand side array
pivot	Pivoting positions
X	Pointer to the solution array
n	Size of matrix A

#### Returns

SUCCESS if succeed, RUN\_FAIL if failed

#### Note

This routine uses Doolittle's method to solve the linear equation Ax = b. This routine is called after the matrix A has been decomposed into a product of a unit lower triangular matrix L and an upper triangular matrix U with pivoting. The solution proceeds by solving the linear equation Ly = b for y and subsequently solving the linear equation Ux = y for x.

# Author

Xuehai Huang

Date

04/02/2009

Definition at line 117 of file lu.c.

# 9.56 memory.c File Reference

Memory allocation and deallocation.

```
#include "fasp.h"
```

#### **Functions**

- void \* fasp\_mem\_calloc (LONG size, INT type)
  - Allocate, initiate, and check memory.
- void \* fasp mem realloc (void \*oldmem, LONG tsize)

Reallocate, initiate, and check memory.

void fasp\_mem\_free (void \*mem)

Free up previous allocated memory body.

void fasp\_mem\_usage ()

Show total allocated memory currently.

SHORT fasp\_mem\_check (void \*ptr, char \*message, INT ERR)

Check wether a point is null or not.

SHORT fasp\_mem\_iludata\_check (ILU\_data \*iludata)

Check wether a ILU\_data has enough work space.

SHORT fasp\_mem\_dcsr\_check (dCSRmat \*A)

Check wether a dCSRmat A has sucessfully allocated memory.

#### **Variables**

- unsigned INT total\_alloc\_mem = 0
- unsigned INT total\_alloc\_count = 0

#### 9.56.1 Detailed Description

Memory allocation and deallocation.

Definition in file memory.c.

# 9.56.2 Function Documentation

9.56.2.1 void \* fasp\_mem\_calloc ( LONG size, INT type )

Allocate, initiate, and check memory.

#### **Parameters**

size	Number of memory blocks
type	Size of memory blocks

#### Returns

Void pointer to the allocated memory

#### **Author**

Chensong Zhang

#### Date

2010/08/12

Modified by Chunsheng Feng on 07/23/2013 Modified by Chunsheng Feng on 07/30/2013 Modified by Chensong Zhang on 07/30/2013: return warning if failed

Definition at line 56 of file memory.c.

9.56.2.2 SHORT fasp\_mem\_check ( void \* ptr, char \* message, INT ERR )

Check wether a point is null or not.

#### **Parameters**

ptr	Void pointer to be checked
message	Error message to print
ERR	Integer error code

Returns

SUCCESS or error code

**Author** 

Chensong Zhang

Date

11/16/2009

Definition at line 189 of file memory.c.

9.56.2.3 SHORT fasp\_mem\_dcsr\_check ( dCSRmat \* A )

Check wether a dCSRmat A has sucessfully allocated memory.

**Parameters** 

Α	Pointer to be cheked

Returns

SUCCESS if success, else ERROR message (negative value)

**Author** 

Xiaozhe Hu

Date

11/27/09

Definition at line 239 of file memory.c.

9.56.2.4 void fasp\_mem\_free ( void \* mem )

Free up previous allocated memory body.

**Parameters** 

mem	Pointer to the memory body need to be freed

Returns

**NULL** pointer

**Author** 

Chensong Zhang

Date

2010/12/24

Definition at line 142 of file memory.c.

9.56.2.5 SHORT fasp\_mem\_iludata\_check ( ILU\_data \* iludata )

Check wether a ILU\_data has enough work space.

**Parameters** 

_		
	iludata	Pointer to be cheked

Returns

SUCCESS if success, else ERROR (negative value)

**Author** 

Xiaozhe Hu, Chensong Zhang

Date

11/27/09

Definition at line 213 of file memory.c.

9.56.2.6 void \* fasp\_mem\_realloc ( void \* oldmem, LONG type )

Reallocate, initiate, and check memory.

**Parameters** 

oldmem	Pointer to the existing mem block
type	Size of memory blocks

# Returns

Void pointer to the reallocated memory

**Author** 

Chensong Zhang

Date

2010/08/12

Modified by Chunsheng Feng on 07/23/2013 Modified by Chensong Zhang on 07/30/2013: return warning if failed Definition at line 108 of file memory.c.

```
9.56.2.7 void fasp_mem_usage ( )
```

Show total allocated memory currently.

**Author** 

Chensong Zhang

Date

2010/08/12

Definition at line 167 of file memory.c.

#### 9.56.3 Variable Documentation

9.56.3.1 unsigned INT total\_alloc\_count = 0

total allocation times

Definition at line 33 of file memory.c.

9.56.3.2 unsigned INT total\_alloc\_mem = 0

total allocated memory

Definition at line 32 of file memory.c.

# 9.57 message.c File Reference

Output some useful messages.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

# **Functions**

void print\_itinfo (const INT ptrlvl, const INT stop\_type, const INT iter, const REAL relres, const REAL absres, const REAL factor)

Print out iteration information for iterative solvers.

void print\_amgcomplexity (AMG\_data \*mgl, const SHORT prtlvl)

Print complexities of AMG method.

• void print\_amgcomplexity\_bsr (AMG\_data\_bsr \*mgl, const SHORT prtlvl)

Print complexities of AMG method for BSR matrices.

void print\_cputime (const char \*message, const REAL cputime)

Print CPU walltime.

• void print\_message (const INT ptrlvl, const char \*message)

Print output information if necessary.

void fasp\_chkerr (const SHORT status, const char \*fctname)

Check error status and print out error messages before quit.

# 9.57.1 Detailed Description

Output some useful messages.

Note

These routines are meant for internal use only.

Definition in file message.c.

#### 9.57.2 Function Documentation

9.57.2.1 void fasp\_chkerr ( const SHORT status, const char \* fctname )

Check error status and print out error messages before quit.

#### **Parameters**

status	Error status
fctname	Function name where this routine is called

**Author** 

Chensong Zhang

Date

01/10/2012

Definition at line 185 of file message.c.

9.57.2.2 void void print\_amgcomplexity ( AMG\_data \* mgl, const SHORT prtlvl )

Print complexities of AMG method.

#### **Parameters**

mgl	Multilevel hierachy for AMG
prtlvl	How much information to print

**Author** 

Chensong Zhang

Date

11/16/2009

Definition at line 79 of file message.c.

9.57.2.3 void void print\_amgcomplexity\_bsr ( AMG\_data\_bsr \* mgl, const SHORT prtlvl )

Print complexities of AMG method for BSR matrices.

#### **Parameters**

mgl	Multilevel hierachy for AMG
prtlvl	How much information to print

#### Author

Chensong Zhang

Date

05/10/2013

Definition at line 115 of file message.c.

9.57.2.4 void void print\_cputime ( const char \* message, const REAL cputime )

Print CPU walltime.

#### **Parameters**

message	Some string to print out
cputime	Walltime since start to end

#### **Author**

Chensong Zhang

Date

04/10/2012

Definition at line 151 of file message.c.

9.57.2.5 void print\_itinfo ( const INT ptrlvl, const INT stop\_type, const INT iter, const REAL relres, const REAL absres, const REAL factor )

Print out iteration information for iterative solvers.

#### **Parameters**

ptrlvl	Level for output
stop_type	Type of stopping criteria
iter	Number of iterations
relres	Relative residual of different kinds
absres	Absolute residual of different kinds
factor	Contraction factor

# Author

Chensong Zhang

Date

11/16/2009

Modified by Chensong Zhang on 03/28/2013: Output initial guess Modified by Chensong Zhang on 04/05/2013: Fix a typo

Definition at line 36 of file message.c.

9.57.2.6 void print\_message ( const INT ptrlvl, const char \* message )

Print output information if necessary.

#### **Parameters**

ptrlvl	Level for output
message	Error message to print

#### **Author**

Chensong Zhang

Date

11/16/2009

Definition at line 168 of file message.c.

# 9.58 messages.h File Reference

Definition of all kinds of messages, including error messages, solver types, etc.

# **Macros**

• #define TRUE 1

Definition of logic type.

- #define FALSE 0
- #define ON 1

Definition of switch.

- #define OFF 0
- #define PRINT\_NONE 0

Print level for all subroutines - not including DEBUG output.

- #define PRINT\_MIN 1
- #define PRINT\_SOME 2
- #define PRINT MORE 4
- #define PRINT\_MOST 8
- #define PRINT\_ALL 10
- #define MAT\_FREE 0

Definition of matrix format.

#define MAT CSR 1

- #define MAT\_BSR 2
- #define MAT STR 3
- #define MAT bCSR 4
- #define MAT bBSR 5
- #define MAT CSRL 6
- #define MAT SymCSR 7
- #define ERROR OPEN FILE -10

Definition of return status and error messages.

- #define ERROR WRONG FILE -11
- #define ERROR INPUT PAR -13
- #define ERROR\_REGRESS -14
- #define ERROR\_NUM\_BLOCKS -18
- #define ERROR\_MISC -19
- #define ERROR ALLOC MEM -20
- #define ERROR DATA STRUCTURE -21
- #define ERROR DATA ZERODIAG -22
- #define ERROR DUMMY VAR -23
- #define ERROR AMG INTERP TYPE -30
- #define ERROR\_AMG\_SMOOTH\_TYPE -31
- #define ERROR AMG COARSE TYPE -32
- #define ERROR AMG COARSEING -33
- #define ERROR\_SOLVER\_TYPE -40
- #define ERROR SOLVER PRECTYPE -41
- #define ERROR\_SOLVER\_STAG -42
- #define ERROR SOLVER SOLSTAG -43
- #define ERROR\_SOLVER\_TOLSMALL -44
- #define ERROR\_SOLVER\_ILUSETUP -45
- #define ERROR SOLVER MISC -46
- #define ERROR SOLVER MAXIT -48
- #define ERROR SOLVER EXIT -49
- #define ERROR QUAD TYPE -60
- #define ERROR\_QUAD\_DIM -61
- #define RUN FAIL -99
- #define SUCCESS 0
- #define SOLVER\_CG 1

Definition of solver types for iterative methods.

- #define SOLVER BiCGstab 2
- #define SOLVER MinRes 3
- #define SOLVER GMRES 4
- #define SOLVER VGMRES 5
- #define SOLVER VFGMRES 6
- #define SOLVER GCG 7
- #define SOLVER SCG 11
- #define SOLVER\_SBiCGstab 12
- #define SOLVER\_SMinRes 13
- #define SOLVER SGMRES 14
- #define SOLVER SVGMRES 15
- #define SOLVER\_SVFGMRES 16
- #define SOLVER\_SGCG 17
- #define SOLVER AMG 21

- #define SOLVER\_FMG 22
- #define SOLVER SUPERLU 31

Definition of solver types for direct methods (requires external libs)

- #define SOLVER UMFPACK 32
- #define SOLVER MUMPS 33
- #define STOP REL RES 1

Definition of iterative solver stopping criteria types.

- #define STOP\_REL\_PRECRES 2
- #define STOP\_MOD\_REL\_RES 3
- #define PREC NULL 0

Definition of preconditioner type for iterative methods.

- #define PREC DIAG 1
- #define PREC AMG 2
- #define PREC\_FMG 3
- #define PREC\_ILU 4
- #define PREC SCHWARZ 5
- #define CLASSIC\_AMG 1

Definition of AMG types.

- #define SA\_AMG 2
- #define UA AMG 3
- #define V\_CYCLE 1

Definition of cycle types.

- #define W CYCLE 2
- #define AMLI CYCLE 3
- #define NL AMLI CYCLE 4
- #define SMOOTHER\_JACOBI 1

Definition of standard smoother types.

- #define SMOOTHER GS 2
- #define SMOOTHER SGS 3
- #define SMOOTHER CG 4
- #define SMOOTHER SOR 5
- #define SMOOTHER\_SSOR 6
- #define SMOOTHER\_GSOR 7
- #define SMOOTHER\_SGSOR 8
- #define SMOOTHER POLY 9
- #define SMOOTHER\_L1DIAG 10
- #define SMOOTHER\_BLKOIL 11

Definition of specialized smoother types.

• #define COARSE\_RS 1

Definition of coarsening types.

- #define COARSE\_CR 3
- #define COARSE AC 4
- #define INTERP\_DIR 1

Definition of interpolation types.

- #define INTERP\_STD 2
- #define INTERP\_ENG 3
- #define UNPT -1

Type of vertices (dofs) for C/F splitting.

#define FGPT 0

- #define CGPT 1
- #define ISPT 2
- #define NO\_ORDER 0

Definition of smoothing order.

- #define CF ORDER 1
- #define USERDEFINED 0

Type of ordering for smoothers.

- #define CPFIRST 1
- #define FPFIRST -1
- #define ASCEND 12
- #define DESCEND 21
- #define ILUk 1

Type of ILU methods.

- #define ILUt 2
- #define ILUtp 3

### 9.58.1 Detailed Description

Definition of all kinds of messages, including error messages, solver types, etc.

#### Note

This is internal use only.

Created by Chensong Zhang on 03/20/2010. Modified by Chensong Zhang on 12/06/2011. Modified by Chensong Zhang on 12/25/2011. Modified by Chensong Zhang on 04/22/2012. Modified by Ludmil Zikatanov on 02/15/2013: CG -> SMOOTHER\_CG. Modified by Chensong Zhang on 02/16/2013: GS -> SMOOTHER\_GS, etc. Modified by Chensong Zhang on 04/09/2013: Add safe krylov methods.

Modified by Chensong Zhang on 09/22/2013: Clean up Doxygen.

Definition in file messages.h.

#### 9.58.2 Macro Definition Documentation

9.58.2.1 #define AMLI\_CYCLE 3

AMLI-cycle

Definition at line 151 of file messages.h.

9.58.2.2 #define ASCEND 12

Asscending order

Definition at line 207 of file messages.h.

9.58.2.3 #define CF\_ORDER 1

C/F order smoothing

Definition at line 199 of file messages.h.

9.58.2.4 #define CGPT 1

coarse grid points

Definition at line 192 of file messages.h.

9.58.2.5 #define CLASSIC\_AMG 1

Definition of AMG types.

classic AMG

Definition at line 142 of file messages.h.

9.58.2.6 #define COARSE\_AC 4

Aggressive coarsening

Definition at line 178 of file messages.h.

9.58.2.7 #define COARSE\_CR 3

Compatible relaxation

Definition at line 177 of file messages.h.

9.58.2.8 #define COARSE\_RS 1

Definition of coarsening types.

Classical coarsening

Definition at line 176 of file messages.h.

9.58.2.9 #define CPFIRST 1

C-points first order

Definition at line 205 of file messages.h.

9.58.2.10 #define DESCEND 21

Dsscending order

Definition at line 208 of file messages.h.

9.58.2.11 #define ERROR\_ALLOC\_MEM -20

fail to allocate memory

Definition at line 67 of file messages.h.

9.58.2.12 #define ERROR\_AMG\_COARSE\_TYPE -32

unknown coarsening type

Definition at line 74 of file messages.h.

9.58.2.13 #define ERROR\_AMG\_COARSEING -33

coarsening step failed to complete

Definition at line 75 of file messages.h.

9.58.2.14 #define ERROR\_AMG\_INTERP\_TYPE -30

unknown interpolation type

Definition at line 72 of file messages.h.

9.58.2.15 #define ERROR\_AMG\_SMOOTH\_TYPE -31

unknown smoother type

Definition at line 73 of file messages.h.

9.58.2.16 #define ERROR\_DATA\_STRUCTURE -21

matrix or vector structures

Definition at line 68 of file messages.h.

9.58.2.17 #define ERROR\_DATA\_ZERODIAG -22

matrix has zero diagonal entries

Definition at line 69 of file messages.h.

9.58.2.18 #define ERROR\_DUMMY\_VAR -23

unexpected input data

Definition at line 70 of file messages.h.

9.58.2.19 #define ERROR\_INPUT\_PAR -13

wrong input argument

Definition at line 62 of file messages.h.

9.58.2.20 #define ERROR\_MISC -19

other error

Definition at line 65 of file messages.h.

9.58.2.21 #define ERROR\_NUM\_BLOCKS -18

wrong number of blocks

Definition at line 64 of file messages.h.

9.58.2.22 #define ERROR\_OPEN\_FILE -10

Definition of return status and error messages.

fail to open a file

Definition at line 60 of file messages.h.

9.58.2.23 #define ERROR\_QUAD\_DIM -61

unsupported quadrature dim

Definition at line 88 of file messages.h.

9.58.2.24 #define ERROR\_QUAD\_TYPE -60

unknown quadrature type

Definition at line 87 of file messages.h.

9.58.2.25 #define ERROR\_REGRESS -14

regression test fail

Definition at line 63 of file messages.h.

9.58.2.26 #define ERROR\_SOLVER\_EXIT -49

solver does not quit successfully

Definition at line 85 of file messages.h.

9.58.2.27 #define ERROR\_SOLVER\_ILUSETUP -45

ILU setup error

Definition at line 82 of file messages.h.

9.58.2.28 #define ERROR\_SOLVER\_MAXIT -48

maximal iteration number exceeded

Definition at line 84 of file messages.h.

9.58.2.29 #define ERROR\_SOLVER\_MISC -46

misc solver error during run time

Definition at line 83 of file messages.h.

9.58.2.30 #define ERROR\_SOLVER\_PRECTYPE -41

unknow precond type

Definition at line 78 of file messages.h.

9.58.2.31 #define ERROR\_SOLVER\_SOLSTAG -43

solver's solution is too small

Definition at line 80 of file messages.h.

9.58.2.32 #define ERROR\_SOLVER\_STAG -42

solver stagnates

Definition at line 79 of file messages.h.

9.58.2.33 #define ERROR\_SOLVER\_TOLSMALL -44

solver's tolerance is too small

Definition at line 81 of file messages.h.

9.58.2.34 #define ERROR\_SOLVER\_TYPE -40

unknown solver type

Definition at line 77 of file messages.h.

9.58.2.35 #define ERROR\_WRONG\_FILE -11

input contains wrong format

Definition at line 61 of file messages.h.

9.58.2.36 #define FALSE 0

logic FALSE

Definition at line 27 of file messages.h.

9.58.2.37 #define FGPT 0

fine grid points

Definition at line 191 of file messages.h.

9.58.2.38 #define FPFIRST -1

F-points first order

Definition at line 206 of file messages.h.

9.58.2.39 #define ILUk 1

Type of ILU methods.

**ILUk** 

Definition at line 213 of file messages.h.

9.58.2.40 #define ILUt 2

**ILUt** 

Definition at line 214 of file messages.h.

9.58.2.41 #define ILUtp 3

**ILUtp** 

Definition at line 215 of file messages.h.

9.58.2.42 #define INTERP\_DIR 1

Definition of interpolation types.

Direct interpolation

Definition at line 183 of file messages.h.

9.58.2.43 #define INTERP\_ENG 3

energy minimization interp in C

Definition at line 185 of file messages.h.

9.58.2.44 #define INTERP\_STD 2

Standard interpolation

Definition at line 184 of file messages.h.

9.58.2.45 #define ISPT 2

isolated points

Definition at line 193 of file messages.h.

9.58.2.46 #define MAT\_bBSR 5

block matrix of BSR for borded systems

Definition at line 53 of file messages.h.

9.58.2.47 #define MAT\_bCSR 4

block matrix of CSR

Definition at line 52 of file messages.h.

9.58.2.48 #define MAT\_BSR 2

blockwise compressed sparse row

Definition at line 50 of file messages.h.

9.58.2.49 #define MAT\_CSR 1

compressed sparse row

Definition at line 49 of file messages.h.

9.58.2.50 #define MAT\_CSRL 6

modified CSR to reduce cache missing

Definition at line 54 of file messages.h.

9.58.2.51 #define MAT\_FREE 0

Definition of matrix format.

matrix-free format: only mxv action

Definition at line 48 of file messages.h.

9.58.2.52 #define MAT\_STR 3

structured sparse matrix

Definition at line 51 of file messages.h.

9.58.2.53 #define MAT\_SymCSR 7

symmetric CSR format

Definition at line 55 of file messages.h.

9.58.2.54 #define NL\_AMLI\_CYCLE 4

Nonlinear AMLI-cycle

Definition at line 152 of file messages.h.

9.58.2.55 #define NO\_ORDER 0

Definition of smoothing order.

Natural order smoothing

Definition at line 198 of file messages.h.

9.58.2.56 #define OFF 0

turn off certain parameter

Definition at line 33 of file messages.h.

9.58.2.57 #define ON 1

Definition of switch.

turn on certain parameter

Definition at line 32 of file messages.h.

9.58.2.58 #define PREC\_AMG 2

with AMG precond

Definition at line 134 of file messages.h.

9.58.2.59 #define PREC\_DIAG 1

with diagonal precond

Definition at line 133 of file messages.h.

9.58.2.60 #define PREC\_FMG 3

with full AMG precond

Definition at line 135 of file messages.h.

9.58.2.61 #define PREC\_ILU 4

with ILU precond

Definition at line 136 of file messages.h.

9.58.2.62 #define PREC\_NULL 0

Definition of preconditioner type for iterative methods.

with no precond

Definition at line 132 of file messages.h.

9.58.2.63 #define PREC\_SCHWARZ 5

with Schwarz preconditioner

Definition at line 137 of file messages.h.

9.58.2.64 #define PRINT\_ALL 10

everything: all printouts allowed

Definition at line 43 of file messages.h.

9.58.2.65 #define PRINT\_MIN 1

quiet: minimal print, like convergence

Definition at line 39 of file messages.h.

9.58.2.66 #define PRINT\_MORE 4

more: print more useful information

Definition at line 41 of file messages.h.

9.58.2.67 #define PRINT\_MOST 8

most: maximal printouts, no disk files

Definition at line 42 of file messages.h.

9.58.2.68 #define PRINT\_NONE 0

Print level for all subroutines – not including DEBUG output.

slient: no printout at all

Definition at line 38 of file messages.h.

9.58.2.69 #define PRINT\_SOME 2

some: print cpu time, iteration number Definition at line 40 of file messages.h. 9.58.2.70 #define RUN\_FAIL -99

general failure

Definition at line 90 of file messages.h.

9.58.2.71 #define SA\_AMG 2

smoothed aggregation AMG

Definition at line 143 of file messages.h.

9.58.2.72 #define SMOOTHER\_BLKOIL 11

Definition of specialized smoother types.

Used in monolithic AMG for black-oil

Definition at line 171 of file messages.h.

9.58.2.73 #define SMOOTHER\_CG 4

CG as a smoother

Definition at line 160 of file messages.h.

9.58.2.74 #define SMOOTHER\_GS 2

Gauss-Seidel smoother

Definition at line 158 of file messages.h.

9.58.2.75 #define SMOOTHER GSOR 7

GS + SOR smoother

Definition at line 163 of file messages.h.

9.58.2.76 #define SMOOTHER\_JACOBI 1

Definition of standard smoother types.

Jacobi smoother

Definition at line 157 of file messages.h.

9.58.2.77 #define SMOOTHER\_L1DIAG 10

L1 norm diagonal scaling smoother

Definition at line 166 of file messages.h.

9.58.2.78 #define SMOOTHER\_POLY 9

Polynomial smoother

Definition at line 165 of file messages.h.

9.58.2.79 #define SMOOTHER\_SGS 3

symm Gauss-Seidel smoother

Definition at line 159 of file messages.h.

9.58.2.80 #define SMOOTHER SGSOR 8

SGS + SSOR smoother

Definition at line 164 of file messages.h.

9.58.2.81 #define SMOOTHER\_SOR 5

SOR smoother

Definition at line 161 of file messages.h.

9.58.2.82 #define SMOOTHER\_SSOR 6

SSOR smoother

Definition at line 162 of file messages.h.

9.58.2.83 #define SOLVER\_AMG 21

AMG as an iterative solver

Definition at line 112 of file messages.h.

9.58.2.84 #define SOLVER\_BiCGstab 2

Biconjugate Gradient Stabilized

Definition at line 97 of file messages.h.

9.58.2.85 #define SOLVER\_CG 1

Definition of solver types for iterative methods.

Conjugate Gradient

Definition at line 96 of file messages.h.

9.58.2.86 #define SOLVER\_FMG 22

Full AMG as an solver

Definition at line 113 of file messages.h.

9.58.2.87 #define SOLVER\_GCG 7

Generalized Conjugate Gradient

Definition at line 102 of file messages.h.

9.58.2.88 #define SOLVER\_GMRES 4

Generalized Minimal Residual

Definition at line 99 of file messages.h.

9.58.2.89 #define SOLVER\_MinRes 3

Minimal Residual

Definition at line 98 of file messages.h.

9.58.2.90 #define SOLVER\_MUMPS 33

MUMPS Direct Solver

Definition at line 120 of file messages.h.

9.58.2.91 #define SOLVER\_SBiCGstab 12

BiCGstab with safe net

Definition at line 105 of file messages.h.

9.58.2.92 #define SOLVER\_SCG 11

Conjugate Gradient with safe net

Definition at line 104 of file messages.h.

9.58.2.93 #define SOLVER\_SGCG 17

GCG with safe net

Definition at line 110 of file messages.h.

9.58.2.94 #define SOLVER\_SGMRES 14

GMRes with safe net

Definition at line 107 of file messages.h.

9.58.2.95 #define SOLVER\_SMinRes 13

MinRes with safe net

Definition at line 106 of file messages.h.

9.58.2.96 #define SOLVER\_SUPERLU 31

Definition of solver types for direct methods (requires external libs)

SuperLU Direct Solver

Definition at line 118 of file messages.h.

9.58.2.97 #define SOLVER\_SVFGMRES 16

Variable-restart FGMRES with safe net

Definition at line 109 of file messages.h.

9.58.2.98 #define SOLVER\_SVGMRES 15

Variable-restart GMRES with safe net

Definition at line 108 of file messages.h.

9.58.2.99 #define SOLVER\_UMFPACK 32

**UMFPack Direct Solver** 

Definition at line 119 of file messages.h.

9.58.2.100 #define SOLVER\_VFGMRES 6

Variable Restarting Flexible GMRES

Definition at line 101 of file messages.h.

9.58.2.101 #define SOLVER\_VGMRES 5

Variable Restarting GMRES

Definition at line 100 of file messages.h.

9.58.2.102 #define STOP\_MOD\_REL\_RES 3

modified relative residual ||r||/||x||

Definition at line 127 of file messages.h.

9.58.2.103 #define STOP\_REL\_PRECRES 2

relative B-residual ||r||\_B/||b||\_B

Definition at line 126 of file messages.h.

9.58.2.104 #define STOP\_REL\_RES 1

Definition of iterative solver stopping criteria types.

relative residual ||r||/||b||

Definition at line 125 of file messages.h.

9.58.2.105 #define SUCCESS 0

return from funtion successfully

Definition at line 91 of file messages.h.

9.58.2.106 #define TRUE 1

Definition of logic type.

logic TRUE

Definition at line 26 of file messages.h.

9.58.2.107 #define UA\_AMG 3

unsmoothed aggregation AMG

Definition at line 144 of file messages.h.

9.58.2.108 #define UNPT -1

Type of vertices (dofs) for C/F splitting.

undetermined points

Definition at line 190 of file messages.h.

9.58.2.109 #define USERDEFINED 0

Type of ordering for smoothers.

**USERDEFINED** order

Definition at line 204 of file messages.h.

9.58.2.110 #define V\_CYCLE 1

Definition of cycle types.

V-cycle

Definition at line 149 of file messages.h.

```
9.58.2.111 #define W_CYCLE 2
```

W-cycle

Definition at line 150 of file messages.h.

# 9.59 mg\_util.inl File Reference

Routines for algebraic multigrid cycles.

# 9.59.1 Detailed Description

Routines for algebraic multigrid cycles.

Definition in file mg\_util.inl.

# 9.60 mgcycle.c File Reference

Abstract non-recursive multigrid cycle.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "forts_ns.h"
#include "mg_util.inl"
```

# **Functions**

- void fasp\_solver\_mgcycle (AMG\_data \*mgl, AMG\_param \*param)
  - Solve Ax=b with non-recursive multigrid cycle.
- void fasp\_solver\_mgcycle\_bsr (AMG\_data\_bsr \*mgl, AMG\_param \*param)

Solve Ax=b with non-recursive multigrid cycle.

# 9.60.1 Detailed Description

Abstract non-recursive multigrid cycle.

Definition in file mgcycle.c.

# 9.60.2 Function Documentation

```
9.60.2.1 void fasp_solver_mgcycle ( AMG_data * mgl, AMG_param * param )
```

Solve Ax=b with non-recursive multigrid cycle.

#### **Parameters**

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

#### **Author**

Chensong Zhang

Date

10/06/2010

Modified by Chensong Zhang on 12/13/2011 Modified by Chensong Zhang on 02/27/2013: update direct solvers. Definition at line 41 of file mgcycle.c.

```
9.60.2.2 void fasp_solver_mgcycle_bsr ( AMG_data_bsr * mgl, AMG_param * param )
```

Solve Ax=b with non-recursive multigrid cycle.

#### **Parameters**

mgl	Pointer to AMG data: AMG_data_bsr
param	Pointer to AMG parameters: AMG_param

### Author

Xiaozhe Hu

Date

08/07/2011

Definition at line 294 of file mgcycle.c.

# 9.61 mgrecur.c File Reference

Abstract multigrid cycle – recursive version.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "mg_util.inl"
```

#### **Functions**

• void fasp\_solver\_mgrecur (AMG\_data \*mgl, AMG\_param \*param, INT level)

Solve Ax=b with recursive multigrid K-cycle.

# 9.61.1 Detailed Description

Abstract multigrid cycle - recursive version.

Definition in file mgrecur.c.

#### 9.61.2 Function Documentation

9.61.2.1 void fasp\_solver\_mgrecur ( AMG data \* mgl, AMG param \* param, INT level )

Solve Ax=b with recursive multigrid K-cycle.

#### **Parameters**

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param
level	Index of the current level

#### **Author**

Xuehai Huang, Chensong Zhang

Date

04/06/2010

Modified by Chensong Zhang on 01/10/2012 Modified by Chensong Zhang on 02/27/2013: update direct solvers. Definition at line 31 of file mgrecur.c.

# 9.62 ordering.c File Reference

A collection of ordering, merging, removing duplicated integers functions.

```
#include "fasp.h"
```

#### **Functions**

INT fasp\_BinarySearch (INT \*list, INT value, INT list\_length)

Binary Search.

INT fasp\_aux\_unique (INT numbers[], INT size)

Remove duplicates in an sorted (ascending order) array.

void fasp\_aux\_merge (INT numbers[], INT work[], INT left, INT mid, INT right)

Merge two sorted arraies.

void fasp\_aux\_msort (INT numbers[], INT work[], INT left, INT right)

Sort the INT array ascendingly with the merge sort algorithm.

void fasp\_aux\_iQuickSort (INT \*a, INT left, INT right)

Sort the array (INT type) ascendingly with the quick sorting algorithm.

void fasp\_aux\_dQuickSort (REAL \*a, INT left, INT right)

Sort the array (REAL type) ascendingly with the quick sorting algorithm.

void fasp\_aux\_iQuickSortIndex (INT \*a, INT left, INT right, INT \*index)

Reorder the index of (INT type) so that 'a' is in ascending order.

void fasp\_aux\_dQuickSortIndex (REAL \*a, INT left, INT right, INT \*index)

Reorder the index of (REAL type) so that 'a' is ascending in such order.

# 9.62.1 Detailed Description

A collection of ordering, merging, removing duplicated integers functions.

Definition in file ordering.c.

## 9.62.2 Function Documentation

9.62.2.1 void fasp\_aux\_dQuickSort ( REAL \* a, INT left, INT right )

Sort the array (REAL type) ascendingly with the quick sorting algorithm.

#### **Parameters**

	а	Pointer to the array needed to be sorted
ĺ	left	Starting index
ĺ	right	Ending index

### **Author**

Zhiyang Zhou

Date

2009/11/28

Note

'left' and 'right' are usually set to be 0 and n-1, respectively where n is the length of 'a'.

Definition at line 238 of file ordering.c.

9.62.2.2 void fasp\_aux\_dQuickSortIndex ( REAL \* a, INT left, INT right, INT \* index )

Reorder the index of (REAL type) so that 'a' is ascending in such order.

# **Parameters**

а	Pointer to the array
left	Starting index
right	Ending index
index	Index of 'a' (out)

## Author

Zhiyang Zhou

Date

2009/12/02

Note

'left' and 'right' are usually set to be 0 and n-1,respectively,where n is the length of 'a'. 'index' should be initialized in the nature order and it has the same length as 'a'.

Definition at line 319 of file ordering.c.

9.62.2.3 void fasp\_aux\_iQuickSort ( INT \* a, INT left, INT right )

Sort the array (INT type) ascendingly with the quick sorting algorithm.

#### **Parameters**

а	Pointer to the array needed to be sorted
left	Starting index
right	Ending index

#### **Author**

Zhiyang Zhou

Date

11/28/2009

Note

'left' and 'right' are usually set to be 0 and n-1, respectively where n is the length of 'a'.

Definition at line 200 of file ordering.c.

9.62.2.4 void fasp\_aux\_iQuickSortIndex ( INT \* a, INT left, INT right, INT \* index )

Reorder the index of (INT type) so that 'a' is in ascending order.

#### **Parameters**

а	Pointer to the array
left	Starting index
right	Ending index
index	Index of 'a' (out)

**Author** 

Zhiyang Zhou

Date

2009/12/02

Note

'left' and 'right' are usually set to be 0 and n-1, respectively, where n is the length of 'a'. 'index' should be initialized in the nature order and it has the same length as 'a'.

Definition at line 278 of file ordering.c.

9.62.2.5 void fasp\_aux\_merge ( INT numbers[], INT work[], INT left, INT mid, INT right )

Merge two sorted arraies.

#### **Parameters**

numbers	Pointer to the array needed to be sorted
work	Pointer to the work array with same size as numbers
left	Starting index of array 1
mid	Starting index of array 2
right	Ending index of array 1 and 2

## Author

Chensong Zhang

Date

11/21/2010

Note

Both arraies are stored in numbers! Arraies should be pre-sorted!

Definition at line 107 of file ordering.c.

9.62.2.6 void fasp\_aux\_msort ( INT numbers[], INT work[], INT left, INT right )

Sort the INT array ascendingly with the merge sort algorithm.

### **Parameters**

numbers	Pointer to the array needed to be sorted
work	Pointer to the work array with same size as numbers
left	Starting index
right	Ending index

## Author

Chensong Zhang

Date

11/21/2010

Note

'left' and 'right' are usually set to be 0 and n-1, respectively

Definition at line 169 of file ordering.c.

9.62.2.7 INT fasp\_aux\_unique ( INT numbers[], INT size )

Remove duplicates in an sorted (ascending order) array.

## **Parameters**

numbers	Pointer to the array needed to be sorted (in/out)
size	Length of the target array

#### Returns

New size after removing duplicates

#### **Author**

Chensong Zhang

Date

11/21/2010

Note

Operation is in place. Does not use any extra or temprary storage.

Definition at line 74 of file ordering.c.

9.62.2.8 INT fasp\_BinarySearch ( INT \* list, INT value, INT list\_length )

Binary Search.

## **Parameters**

list	Pointer to a set of values
value	The target
list_length	Length of the array list

## Returns

The location of value in array list if successed, otherwise, return -1.

## **Author**

Chunsheng Feng

Date

03/01/2011

Definition at line 29 of file ordering.c.

# 9.63 parameters.c File Reference

Initialize, set, or print input data and parameters.

```
#include <stdio.h>
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

void fasp\_param\_init (char \*inputfile, input\_param \*inparam, itsolver\_param \*itsparam, AMG\_param \*amgparam, ILU\_param \*iluparam, Schwarz\_param \*schparam)

Initialize parameters, global variables, etc.

void fasp\_param\_input\_init (input\_param \*inparam)

Initialize input parameters.

void fasp\_param\_amg\_init (AMG\_param \*amgparam)

Initialize AMG parameters.

void fasp\_param\_solver\_init (itsolver\_param \*itsparam)

Initialize itsolver param.

void fasp param ilu init (ILU param \*iluparam)

Initialize ILU parameters.

void fasp param schwarz init (Schwarz param \*schparam)

Initialize Schwarz parameters.

void fasp\_param\_amg\_set (AMG\_param \*param, input\_param \*inparam)

Set AMG param from INPUT.

void fasp\_param\_ilu\_set (ILU\_param \*iluparam, input\_param \*inparam)

Set ILU param with INPUT.

void fasp\_param\_schwarz\_set (Schwarz\_param \*schparam, input\_param \*inparam)

Set Schwarz\_param with INPUT.

void fasp\_param\_solver\_set (itsolver\_param \*itsparam, input\_param \*inparam)

Set itsolver\_param with INPUT.

void fasp\_precond\_data\_null (precond\_data \*pcdata)

Initialize precond\_data.

void fasp\_param\_amg\_to\_prec (precond\_data \*pcdata, AMG\_param \*amgparam)

Set precond\_data with AMG\_param.

void fasp\_param\_prec\_to\_amg (AMG\_param \*amgparam, precond\_data \*pcdata)

Set AMG\_param with precond\_data.

void fasp\_param\_amg\_to\_prec\_bsr (precond\_data\_bsr \*pcdata, AMG\_param \*amgparam)

Set precond\_data\_bsr with AMG\_param.

void fasp\_param\_prec\_to\_amg\_bsr (AMG\_param \*amgparam, precond\_data\_bsr \*pcdata)

Set AMG\_param with precond\_data.

void fasp\_param\_amg\_print (AMG\_param \*param)

Print out AMG parameters.

• void fasp\_param\_ilu\_print (ILU\_param \*param)

Print out ILU parameters.

void fasp\_param\_schwarz\_print (Schwarz\_param \*param)

Print out Schwarz parameters.

void fasp param solver print (itsolver param \*param)

Print out itsolver parameters.

## 9.63.1 Detailed Description

Initialize, set, or print input data and parameters.

Definition in file parameters.c.

# 9.63.2 Function Documentation

9.63.2.1 void fasp\_param\_amg\_init ( AMG\_param \* amgparam )

Initialize AMG parameters.

## **Parameters**

amgparam	Parameters for AMG
----------	--------------------

**Author** 

Chensong Zhang

Date

2010/04/03

Definition at line 153 of file parameters.c.

9.63.2.2 void fasp\_param\_amg\_print ( AMG\_param \* param )

Print out AMG parameters.

**Parameters** 

param	Parameters for AMG
-------	--------------------

**Author** 

Chensong Zhang

Date

2010/03/22

Definition at line 573 of file parameters.c.

9.63.2.3 void fasp\_param\_amg\_set ( AMG\_param \* param, input\_param \* inparam )

Set AMG\_param from INPUT.

# **Parameters**

param	Parameters for AMG
inparam	Input parameters

**Author** 

Chensong Zhang

Date

2010/03/23

Definition at line 275 of file parameters.c.

9.63.2.4 void fasp\_param\_amg\_to\_prec ( precond\_data \* pcdata, AMG\_param \* amgparam )

Set precond\_data with AMG\_param.

## **Parameters**

pcdata	Preconditioning data structure
amgparam	Parameters for AMG

**Author** 

Chensong Zhang

Date

2011/01/10

Definition at line 446 of file parameters.c.

9.63.2.5 void fasp\_param\_amg\_to\_prec\_bsr ( precond\_data\_bsr \* pcdata, AMG\_param \* amgparam )

Set precond\_data\_bsr with AMG\_param.

#### **Parameters**

pcdata	Preconditioning data structure
amgparam	Parameters for AMG

**Author** 

Xiaozhe Hu

Date

02/06/2012

Definition at line 511 of file parameters.c.

9.63.2.6 void fasp\_param\_ilu\_init ( ILU\_param \* iluparam )

Initialize ILU parameters.

## **Parameters**

iluparam	Parameters for ILU

**Author** 

Chensong Zhang

Date

2010/04/06

Definition at line 236 of file parameters.c.

9.63.2.7 void fasp\_param\_ilu\_print ( ILU\_param \* param )

Print out ILU parameters.

## **Parameters**

param	Parameters for ILU
-------	--------------------

## **Author**

Chensong Zhang

Date

2011/12/20

Definition at line 666 of file parameters.c.

9.63.2.8 void fasp\_param\_ilu\_set ( ILU\_param \* iluparam, input\_param \* inparam )

Set ILU\_param with INPUT.

## **Parameters**

iluparam	Parameters for ILU
inparam	Input parameters

# Author

Chensong Zhang

Date

2010/04/03

Definition at line 345 of file parameters.c.

9.63.2.9 void fasp\_param\_init ( char \* inputfile, input\_param \* inparam, itsolver\_param \* itsparam, AMG\_param \* amgparam, ILU\_param \* iluparam, Schwarz\_param \* schparam )

Initialize parameters, global variables, etc.

## **Parameters**

inputfile	Filename of the input file
inparam	Input parameters
itsparam	Iterative solver parameters
amgparam	AMG parameters
iluparam	ILU parameters
schparam	Schwarz parameters

# Author

Chensong Zhang

Date

2010/08/12

Modified by Xiaozhe Hu (01/23/2011): initialize, then set value Modified by Chensong Zhang (09/12/2012): find a bug during debugging in VS08

Definition at line 38 of file parameters.c.

9.63.2.10 void fasp\_param\_input\_init ( input\_param \* inparam )

Initialize input parameters.

**Parameters** 

inparam	Input parameters
---------	------------------

**Author** 

Chensong Zhang

Date

2010/03/20

Definition at line 78 of file parameters.c.

9.63.2.11 void fasp\_param\_prec\_to\_amg ( AMG\_param \* amgparam, precond\_data \* pcdata )

Set AMG\_param with precond\_data.

### **Parameters**

amgparam	Parameters for AMG
pcdata	Preconditioning data structure

Author

Chensong Zhang

Date

2011/01/10

Definition at line 480 of file parameters.c.

9.63.2.12 void fasp\_param\_prec\_to\_amg\_bsr ( AMG\_param \* amgparam, precond\_data\_bsr \* pcdata )

Set AMG\_param with precond\_data.

## **Parameters**

amgparam	Parameters for AMG
pcdata	Preconditioning data structure

**Author** 

Xiaozhe Hu

Date

02/06/2012

Definition at line 544 of file parameters.c.

9.63.2.13 void fasp\_param\_schwarz\_init ( Schwarz\_param \* schparam )

Initialize Schwarz parameters.

**Parameters** 

schparam	Parameters for Schwarz method
----------	-------------------------------

**Author** 

Xiaozhe Hu

Date

05/22/2012

Definition at line 256 of file parameters.c.

9.63.2.14 void fasp\_param\_schwarz\_print ( Schwarz\_param \* param )

Print out Schwarz parameters.

**Parameters** 

param	Parameters for Schwarz

Author

Xiaozhe Hu

Date

05/22/2012

Definition at line 696 of file parameters.c.

9.63.2.15 void fasp\_param\_schwarz\_set ( Schwarz\_param \* schparam, input\_param \* inparam )

Set Schwarz\_param with INPUT.

## **Parameters**

schparam	Parameters for Schwarz method
inparam	Input parameters

**Author** 

Xiaozhe Hu

Date

05/22/2012

Definition at line 367 of file parameters.c.

9.63.2.16 void fasp\_param\_solver\_init ( itsolver\_param \* itsparam )

Initialize itsolver\_param.

## **Parameters**

itsparam	Parameters for iterative solvers
----------	----------------------------------

Author

Chensong Zhang

Date

2010/03/23

Definition at line 215 of file parameters.c.

9.63.2.17 void fasp\_param\_solver\_print ( itsolver\_param \* param )

Print out itsolver parameters.

**Parameters** 

param	Paramters for iterative solvers
-------	---------------------------------

**Author** 

Chensong Zhang

Date

2011/12/20

Definition at line 725 of file parameters.c.

9.63.2.18 void fasp\_param\_solver\_set (itsolver\_param \* itsparam, input\_param \* inparam)

Set itsolver\_param with INPUT.

#### **Parameters**

itsparam	Parameters for iterative solvers
inparam	Input parameters

## **Author**

Chensong Zhang

Date

2010/03/23

Definition at line 387 of file parameters.c.

```
9.63.2.19 void fasp_precond_data_null ( precond_data * pcdata )
```

Initialize precond\_data.

#### **Parameters**

pcdata	Preconditioning data structure
--------	--------------------------------

#### **Author**

Chensong Zhang

Date

2010/03/23

Definition at line 416 of file parameters.c.

# 9.64 pbcgs.c File Reference

Krylov subspace methods - Preconditioned BiCGstab.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

## **Functions**

• INT fasp\_solver\_dcsr\_pbcgs (dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop type, const SHORT print level)

Preconditioned BiCGstab method for solving Au=b.

• INT fasp\_solver\_dbsr\_pbcgs (dBSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned BiCGstab method for solving Au=b.

• INT fasp\_solver\_bdcsr\_pbcgs (block\_dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop type, const SHORT print level)

A preconditioned BiCGstab method for solving Au=b.

INT fasp\_solver\_dstr\_pbcgs (dSTRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop type, const SHORT print level)

Preconditioned BiCGstab method for solving Au=b.

#### 9.64.1 Detailed Description

Krylov subspace methods – Preconditioned BiCGstab. Abstract algorithm

PBICGStab method to solve A\*x=b is to generate {x k} to approximate x

Note: We generate a series of {p\_k} such that V\_k=span{p\_1,...,p\_k}.

Step 0. Given A, b, x 0, M

Step 1. Compute residual  $r_0 = b-A*x_0$  and convergence check;

Step 2. Initialization  $z_0 = M^{-1}*r_0$ ,  $p_0=z_0$ ;

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r k,z k,p k);
- update solution: x\_{k+1} = x\_k + alpha\*p\_k;
- · perform stagnation check;
- update residual: r\_{k+1} = r\_k alpha\*(A\*p\_k);
- · perform residual check;
- obtain p\_{k+1} using {p\_0, p\_1, ..., p\_k};
- · prepare for next iteration;
- · print the result of k-th iteration; END FOR

Convergence check: norm(r)/norm(b) < tol

Stagnation check:

- IF norm(alpha\*p\_k)/norm(x\_{k+1}) < tol\_stag</li>
  - 1. compute  $r=b-A*x \{k+1\}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Stag\_Check ) restart;
- END IF

#### Residual check:

- IF  $norm(r_{k+1})/norm(b) < tol$ 
  - 1. compute the real residual  $r = b-A*x \{k+1\}$ ;
  - 2. convergence check;

- 3. IF ( not converged & restart\_number < Max\_Res\_Check ) restart;
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See spbcgs.c for a safer version

Definition in file pbcgs.c.

# 9.64.2 Function Documentation

9.64.2.1 INT fasp\_solver\_bdcsr\_pbcgs ( block\_dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

A preconditioned BiCGstab method for solving Au=b.

#### **Parameters**

Α	Pointer to the coefficient matrix
b	Pointer to the dvector of right hand side
и	Pointer to the dvector of DOFs
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

## Returns

Number of iterations if converged, error message otherwise

Author

Xiaozhe Hu

Date

05/24/2010

Rewritten by Chensong Zhang on 04/30/2012 Modified by Feiteng Huang on 06/01/2012: fix restart param-init Modified by Chensong Zhang on 03/31/2013

Definition at line 781 of file pbcgs.c.

9.64.2.2 INT fasp\_solver\_dbsr\_pbcgs ( dBSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned BiCGstab method for solving Au=b.

## **Parameters**

Α	Pointer to the coefficient matrix
b	Pointer to the dvector of right hand side
и	Pointer to the dvector of DOFs
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

## **Author**

Chensong Zhang

#### Date

09/09/2009

Rewritten by Chensong Zhang on 04/30/2012 Modified by Feiteng Huang on 06/01/2012: fix restart param-init Modified by Chensong Zhang on 03/31/2013

Definition at line 435 of file pbcgs.c.

9.64.2.3 INT fasp\_solver\_dcsr\_pbcgs ( dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned BiCGstab method for solving Au=b.

#### **Parameters**

A	Pointer to the coefficient matrix
b	Pointer to the dvector of right hand side
и	Pointer to the dvector of DOFs
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

### Returns

Number of iterations if converged, error message otherwise

## **Author**

Chensong Zhang

Date

09/09/2009

Rewritten by Chensong Zhang on 04/30/2012 Modified by Feiteng Huang on 06/01/2012: fix restart param-init Modified by Chensong Zhang on 03/31/2013

Definition at line 89 of file pbcgs.c.

9.64.2.4 INT fasp\_solver\_dstr\_pbcgs ( dSTRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned BiCGstab method for solving Au=b.

#### **Parameters**

Α	Pointer to the coefficient matrix
b	Pointer to the dvector of right hand side
и	Pointer to the dvector of DOFs
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

Author

Zhiyang Zhou

Date

04/25/2010

Rewritten by Chensong Zhang on 04/30/2012 Modified by Feiteng Huang on 06/01/2012: fix restart param-init Modified by Chensong Zhang on 03/31/2013

Definition at line 1127 of file pbcgs.c.

# 9.65 pbcgs\_mf.c File Reference

Krylov subspace methods – Preconditioned BiCGstab (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

## **Functions**

INT fasp\_solver\_pbcgs (mxv\_matfree \*mf, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned BiCGstab method for solving Au=b.

## 9.65.1 Detailed Description

Krylov subspace methods - Preconditioned BiCGstab (matrix free) Abstract algorithm of Krylov method

Krylov method to solve A\*x=b is to generate  $\{x\_k\}$  to approximate x, where  $x\_k$  is the optimal solution in Krylov space

$$V_k=span\{r_0,A*r_0,A^2*r_0,...,A^{k-1}*r_0\},$$

under some inner product.

For the implementation, we generate a series of {p\_k} such that V\_k=span{p\_1,...,p\_k}. Details:

Step 0. Given A, b, x\_0, M

Step 1. Compute residual  $r_0 = b-A*x_0$  and convergence check;

Step 2. Initialization z  $0 = M^{-1}*r 0$ , p 0=z 0;

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r\_k,z\_k,p\_k);
- update solution: x\_{k+1} = x\_k + alpha\*p\_k;
- · perform stagnation check;
- update residual: r {k+1} = r k alpha\*(A\*p k);
- · perform residual check;
- obtain p\_{k+1} using {p\_0, p\_1, ..., p\_k};
- · prepare for next iteration;
- print the result of k-th iteration; END FOR

Convergence check is: norm(r)/norm(b) < tol

Stagnation check is like following:

- IF  $norm(alpha*p_k)/norm(x_{k+1}) < tol_stag$ 
  - 1. compute  $r=b-A*x_{k+1}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart number < Max Stag Check ) restart;
- END IF

Residual check is like following:

- IF  $norm(r_{k+1})/norm(b) < tol$ 
  - 1. compute the real residual  $r = b-A*x \{k+1\}$ ;

- 2. convergence check;
- 3. IF ( not converged & restart\_number < Max\_Res\_Check ) restart;
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM

Definition in file pbcgs\_mf.c.

## 9.65.2 Function Documentation

9.65.2.1 INT fasp\_solver\_pbcgs ( mxv\_matfree \* mf, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned BiCGstab method for solving Au=b.

#### **Parameters**

mf	Pointer to mxv_matfree: the spmv operation
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

### Returns

Number of iterations if converged, error message otherwise

### **Author**

Chensong Zhang

Date

09/09/2009

Rewritten by Chensong Zhang on 04/30/2012 Modified by Feiteng Huang on 06/01/2012: fix restart param-init Modified by Feiteng Huang on 09/26/2012, (mmatrix free)

Definition at line 91 of file pbcgs\_mf.c.

# 9.66 pcg.c File Reference

Krylov subspace methods – Preconditioned conjugate gradient.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

#### **Functions**

INT fasp\_solver\_dcsr\_pcg (dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned conjugate gradient method for solving Au=b.

 INT fasp\_solver\_bdcsr\_pcg (block\_dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned conjugate gradient method for solving Au=b.

INT fasp\_solver\_dstr\_pcg (dSTRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned conjugate gradient method for solving Au=b.

### 9.66.1 Detailed Description

Krylov subspace methods - Preconditioned conjugate gradient. Abstract algorithm

PCG method to solve A\*x=b is to generate {x\_k} to approximate x

Step 0. Given A, b, x 0, M

Step 1. Compute residual  $r_0 = b-A*x_0$  and convergence check;

Step 2. Initialization  $z_0 = M^{(-1)}*r_0, p_0=z_0$ ;

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r\_k,z\_k,p\_k);
- update solution: x\_{k+1} = x\_k + alpha\*p\_k;
- · perform stagnation check;
- update residual: r\_{k+1} = r\_k alpha\*(A\*p\_k);
- · perform residual check;
- obtain p\_{k+1} using {p\_0, p\_1, ..., p\_k};
- · prepare for next iteration;
- print the result of k-th iteration; END FOR

Convergence check: norm(r)/norm(b) < tol

Stagnation check:

- IF norm(alpha\*p\_k)/norm(x\_{k+1}) < tol\_stag</li>
  - 1. compute  $r=b-A*x_{k+1}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Stag\_Check ) restart;
- END IF

## Residual check:

• IF norm(r {k+1})/norm(b) < tol

- 1. compute the real residual  $r = b-A*x_{k+1}$ ;
- 2. convergence check;
- 3. IF ( not converged & restart\_number < Max\_Res\_Check ) restart;
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See spcg.c for a safer version

Definition in file pcg.c.

## 9.66.2 Function Documentation

9.66.2.1 INT fasp\_solver\_bdcsr\_pcg ( block\_dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned conjugate gradient method for solving Au=b.

#### **Parameters**

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

### Returns

Number of iterations if converged, error message otherwise

#### **Author**

Xiaozhe Hu

Date

05/24/2010

Modified by Chensong Zhang on 04/30/2012 Modified by Chensong Zhang on 03/28/2013 Definition at line 367 of file pcg.c.

9.66.2.2 INT fasp\_solver\_dcsr\_pcg ( dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned conjugate gradient method for solving Au=b.

## **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

#### **Returns**

Number of iterations if converged, error message otherwise

## **Author**

Chensong Zhang, Xiaozhe Hu, Shiquan Zhang

Date

05/06/2010

Modified by Chensong Zhang on 04/30/2012 Modified by Chensong Zhang on 03/28/2013 Definition at line 85 of file pcg.c.

9.66.2.3 INT fasp\_solver\_dstr\_pcg ( dSTRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned conjugate gradient method for solving Au=b.

### **Parameters**

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

### Returns

Number of iterations if converged, error message otherwise

## Author

Zhiyang Zhou

Date

04/25/2010

Modified by Chensong Zhang on 04/30/2012 Modified by Chensong Zhang on 03/28/2013 Definition at line 648 of file pcg.c.

# 9.67 pcg\_mf.c File Reference

Krylov subspace methods – Preconditioned conjugate gradient (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

#### **Functions**

INT fasp\_solver\_pcg (mxv\_matfree \*mf, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned conjugate gradient (CG) method for solving Au=b.

## 9.67.1 Detailed Description

Krylov subspace methods - Preconditioned conjugate gradient (matrix free) Abstract algorithm

PCG method to solve A\*x=b is to generate  $\{x\_k\}$  to approximate x

```
Step 0. Given A, b, x 0, M
```

Step 1. Compute residual  $r_0 = b-A*x_0$  and convergence check;

```
Step 2. Initialization z_0 = M^{(-1)}*r_0, p_0=z_0;
```

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r\_k,z\_k,p\_k);
- update solution: x\_{k+1} = x\_k + alpha\*p\_k;
- · perform stagnation check;
- update residual: r\_{k+1} = r\_k alpha\*(A\*p\_k);
- · perform residual check;
- obtain p\_{k+1} using {p\_0, p\_1, ..., p\_k};
- · prepare for next iteration;
- · print the result of k-th iteration; END FOR

Convergence check is: norm(r)/norm(b) < tol

Stagnation check is like following:

- IF norm(alpha\*p\_k)/norm(x\_{k+1}) < tol\_stag</li>
  - 1. compute  $r=b-A*x \{k+1\}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Stag\_Check ) restart;

• END IF

Residual check is like following:

- IF  $norm(r_{k+1})/norm(b) < tol$ 
  - 1. compute the real residual  $r = b-A*x_{k+1}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Res\_Check ) restart;
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM

Definition in file pcg\_mf.c.

# 9.67.2 Function Documentation

9.67.2.1 INT fasp\_solver\_pcg ( mxv\_matfree \* mf, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned conjugate gradient (CG) method for solving Au=b.

### **Parameters**

mf	Pointer to mxv_matfree: the spmv operation
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

### **Author**

Chensong Zhang, Xiaozhe Hu, Shiquan Zhang

Date

05/06/2010

Modified by Chensong Zhang on 04/30/2012 Modified by Feiteng Huang on 09/19/2012, (matrix free) Definition at line 87 of file pcg\_mf.c.

# 9.68 pgcg.c File Reference

Krylov subspace methods - Preconditioned Generalized CG.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

## **Functions**

INT fasp\_solver\_dcsr\_pgcg (dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned generilzed conjugate gradient (GCG) method for solving Au=b.

# 9.68.1 Detailed Description

Krylov subspace methods – Preconditioned Generalized CG.

#### Note

Refer to Concus, P. and Golub, G.H. and O'Leary, D.P. A Generalized Conjugate Gradient Method for the Numerical: Solution of Elliptic Partial Differential Equations, Computer Science Department, Stanford University, 1976

Definition in file pgcg.c.

## 9.68.2 Function Documentation

9.68.2.1 INT fasp\_solver\_dcsr\_pgcg ( dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned generilzed conjugate gradient (GCG) method for solving Au=b.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

## Returns

Number of iterations if converged, error message otherwise

**Author** 

Xiaozhe Hu

Date

01/01/2012

Note

Not completely implemented yet! - Chensong

Modified by Chensong Zhang on 05/01/2012

Definition at line 46 of file pgcg.c.

# 9.69 pgcg\_mf.c File Reference

Krylov subspace methods – Preconditioned Generalized CG (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver util.inl"
```

# **Functions**

INT fasp\_solver\_pgcg (mxv\_matfree \*mf, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned generilzed conjugate gradient (GCG) method for solving Au=b.

# 9.69.1 Detailed Description

Krylov subspace methods – Preconditioned Generalized CG (matrix free)

Note

Refer to Concus, P. and Golub, G.H. and O'Leary, D.P. A Generalized Conjugate Gradient Method for the Numerical: Solution of Elliptic Partial Differential Equations, Computer Science Department, Stanford University, 1976

Definition in file pgcg mf.c.

#### 9.69.2 Function Documentation

9.69.2.1 INT fasp\_solver\_pgcg ( mxv\_matfree \* mf, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned generilzed conjugate gradient (GCG) method for solving Au=b.

#### **Parameters**

mf	Pointer to mxv_matfree: the spmv operation
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type – Not implemented
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

#### **Author**

Xiaozhe Hu

#### Date

01/01/2012

#### Note

Not completely implemented yet! -Chensong

Modified by Chensong Zhang on 05/01/2012 Modified by Feiteng Huang on 09/26/2012, (matrix free) Definition at line 47 of file pgcg\_mf.c.

# 9.70 pgmres.c File Reference

Krylov subspace methods - Preconditioned GMRes.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

### **Functions**

 INT fasp\_solver\_dcsr\_pgmres (dCSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Preconditioned GMRES method for solving Au=b.

• INT fasp\_solver\_bdcsr\_pgmres (block\_dCSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop type, const SHORT print level)

Preconditioned GMRES method for solving Au=b.

 INT fasp\_solver\_dbsr\_pgmres (dBSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level) Preconditioned GMRES method for solving Au=b.

• INT fasp\_solver\_dstr\_pgmres (dSTRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Preconditioned GMRES method for solving Au=b.

# 9.70.1 Detailed Description

Krylov subspace methods – Preconditioned GMRes.

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See also pvgmres.c for a variable restarting version.

See spgmres.c for a safer version

Definition in file pgmres.c.

## 9.70.2 Function Documentation

9.70.2.1 INT fasp\_solver\_bdcsr\_pgmres ( block\_dCSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Preconditioned GMRES method for solving Au=b.

#### **Parameters**

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

Author

Xiaozhe Hu

Date

05/24/2010

Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/05/2013: add stop\_type and safe check

Definition at line 345 of file pgmres.c.

9.70.2.2 INT fasp\_solver\_dbsr\_pgmres ( dBSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Preconditioned GMRES method for solving Au=b.

## **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

## **Author**

Zhiyang Zhou

#### Date

2010/12/21

Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/05/2013: add stop\_type and safe check

Definition at line 641 of file pgmres.c.

9.70.2.3 INT fasp\_solver\_dcsr\_pgmres ( dCSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Preconditioned GMRES method for solving Au=b.

# Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

## Returns

Number of iterations if converged, error message otherwise

# **Author**

Zhiyang Zhou

Date

2010/11/28

Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/05/2013: add stop\_type and safe check Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate

Definition at line 49 of file pgmres.c.

9.70.2.4 INT fasp\_solver\_dstr\_pgmres ( dSTRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Preconditioned GMRES method for solving Au=b.

#### **Parameters**

A	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

### Author

Zhiyang Zhou

Date

2010/11/28

Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/05/2013: add stop\_type and safe check

Definition at line 937 of file pgmres.c.

# 9.71 pgmres\_mf.c File Reference

Krylov subspace methods – Preconditioned GMRes (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

#### **Functions**

 INT fasp\_solver\_pgmres (mxv\_matfree \*mf, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Solve "Ax=b" using PGMRES (right preconditioned) iterative method.

## 9.71.1 Detailed Description

Krylov subspace methods – Preconditioned GMRes (matrix free)

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM Refer to A.H. Baker, E.R. Jessup, and Tz.V. Kolev A Simple Strategy for Varying the Restart Parameter in GMRE-S(m) Journal of Computational and Applied Mathematics, 230 (2009) pp. 751-761. UCRL-JRNL-235266.

Definition in file pgmres mf.c.

## 9.71.2 Function Documentation

9.71.2.1 INT fasp\_solver\_pgmres ( mxv\_matfree \* mf, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Solve "Ax=b" using PGMRES (right preconditioned) iterative method.

#### **Parameters**

mf	Pointer to mxv_matfree: the spmv operation
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type – DOES not support this parameter
print_level	How much information to print out

### Returns

Number of iterations if converged, error message otherwise

#### **Author**

Zhiyang Zhou

#### Date

2010/11/28

Modified by Chensong Zhang on 05/01/2012 Modified by Feiteng Huang on 09/26/2012, (matrix free) Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate

Definition at line 51 of file pgmres mf.c.

# 9.72 pminres.c File Reference

Krylov subspace methods – Preconditioned minimal residual.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

#### **Functions**

 INT fasp\_solver\_dcsr\_pminres (dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

A preconditioned minimal residual (Minres) method for solving Au=b.

 INT fasp\_solver\_bdcsr\_pminres (block\_dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

A preconditioned minimal residual (Minres) method for solving Au=b.

 INT fasp\_solver\_dstr\_pminres (dSTRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

A preconditioned minimal residual (Minres) method for solving Au=b.

## 9.72.1 Detailed Description

Krylov subspace methods - Preconditioned minimal residual. Abstract algorithm of Krylov method

Krylov method to solve A\*x=b is to generate  $\{x\_k\}$  to approximate x, where  $x\_k$  is the optimal solution in Krylov space

```
V k=span{r 0,A*r 0,A^2*r 0,...,A^{k-1}*r 0},
```

under some inner product.

For the implementation, we generate a series of  $\{p_k\}$  such that  $V_k=span\{p_1,...,p_k\}$ . Details:

```
Step 0. Given A, b, x 0, M
```

Step 1. Compute residual  $r_0 = b-A*x_0$  and convergence check;

```
Step 2. Initialization z 0 = M^{\uparrow} \{-1\} * r \ 0, p \ 0 = z \ 0;
```

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r k,z k,p k);
- update solution: x\_{k+1} = x\_k + alpha\*p\_k;
- · perform stagnation check;
- update residual:  $r_{k+1} = r_k alpha*(A*p_k)$ ;
- · perform residual check;
- obtain p {k+1} using {p 0, p 1, ..., p k};
- · prepare for next iteration;
- print the result of k-th iteration; END FOR

Convergence check: norm(r)/norm(b) < tol

Stagnation check:

- IF  $norm(alpha*p_k)/norm(x_{k+1}) < tol_stag$ 
  - 1. compute  $r=b-A*x_{k+1}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Stag\_Check ) restart;
- END IF

## Residual check:

- IF norm(r\_{k+1})/norm(b) < tol</li>
  - 1. compute the real residual  $r = b-A*x_{k+1}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Res\_Check ) restart;
- END IF

#### Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See spminres.c for a safer version

Definition in file pminres.c.

## 9.72.2 Function Documentation

9.72.2.1 INT fasp\_solver\_bdcsr\_pminres ( block\_dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

A preconditioned minimal residual (Minres) method for solving Au=b.

#### **Parameters**

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

# Returns

Number of iterations if converged, error message otherwise

## **Author**

Chensong Zhang

Date

05/01/2012

Note

Rewritten based on the original version by Xiaozhe Hu 05/24/2010

Modified by Chensong Zhang on 04/09/2013

Definition at line 499 of file pminres.c.

9.72.2.2 INT fasp\_solver\_dcsr\_pminres ( dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

A preconditioned minimal residual (Minres) method for solving Au=b.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

**Author** 

Chensong Zhang

Date

05/01/2012

Note

Rewritten based on the original version by Shiquan Zhang 05/10/2010

Modified by Chensong Zhang on 04/09/2013

Definition at line 93 of file pminres.c.

9.72.2.3 INT fasp\_solver\_dstr\_pminres ( dSTRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

A preconditioned minimal residual (Minres) method for solving Au=b.

#### **Parameters**

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

### Author

Chensong Zhang

Date

04/09/2013

Definition at line 901 of file pminres.c.

# 9.73 pminres\_mf.c File Reference

Krylov subspace methods - Preconditioned minimal residual (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

#### **Functions**

• INT fasp\_solver\_pminres (mxv\_matfree \*mf, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

A preconditioned minimal residual (Minres) method for solving Au=b.

# 9.73.1 Detailed Description

Krylov subspace methods – Preconditioned minimal residual (matrix free) Abstract algorithm of Krylov method Krylov method to solve A\*x=b is to generate  $\{x\_k\}$  to approximate x, where  $x\_k$  is the optimal solution in Krylov space  $V\_k=span\{r\_0,A*r\_0,A^2*r\_0,...,A^k\{k-1\}*r\_0\}$ ,

under some inner product.

For the implementation, we generate a series of {p\_k} such that V\_k=span{p\_1,...,p\_k}. Details:

```
Step 0. Given A, b, x_0, M
```

Step 1. Compute residual r 0 = b-A\*x 0 and convergence check;

Step 2. Initialization  $z_0 = M^{-1}*r_0$ ,  $p_0=z_0$ ;

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r\_k,z\_k,p\_k);
- update solution: x\_{k+1} = x\_k + alpha\*p\_k;
- · perform stagnation check;
- update residual: r\_{k+1} = r\_k alpha\*(A\*p\_k);
- · perform residual check;
- obtain p\_{k+1} using {p\_0, p\_1, ..., p\_k};
- · prepare for next iteration;
- · print the result of k-th iteration; END FOR

Convergence check is: norm(r)/norm(b) < tol

Stagnation check is like following:

- IF norm(alpha\*p\_k)/norm(x\_{k+1}) < tol\_stag</li>
  - compute r=b-A\*x\_{k+1};
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Stag\_Check ) restart;
- END IF

Residual check is like following:

- IF  $norm(r_{k+1})/norm(b) < tol$ 
  - 1. compute the real residual  $r = b-A*x_{k+1}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Res\_Check ) restart;
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM

Definition in file pminres\_mf.c.

### 9.73.2 Function Documentation

9.73.2.1 INT fasp\_solver\_pminres ( mxv\_matfree \* mf, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

A preconditioned minimal residual (Minres) method for solving Au=b.

#### **Parameters**

mf	Pointer to mxv_matfree: the spmv operation
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

### **Author**

Shiquan Zhang

Date

10/24/2010

Rewritten by Chensong Zhang on 05/01/2012 Modified by Feiteng Huang on 09/26/2012, (matrix free) Definition at line 90 of file pminres\_mf.c.

# 9.74 precond\_bsr.c File Reference

Preconditioners for dBSRmat matrices.

```
#include "fasp.h"
#include "fasp_functs.h"
```

# **Functions**

void fasp\_precond\_dbsr\_diag (REAL \*r, REAL \*z, void \*data)

Diagonal preconditioner z=inv(D)\*r.

void fasp\_precond\_dbsr\_diag\_nc2 (REAL \*r, REAL \*z, void \*data)

Diagonal preconditioner z=inv(D)\*r.

void fasp\_precond\_dbsr\_diag\_nc3 (REAL \*r, REAL \*z, void \*data)

Diagonal preconditioner z=inv(D)\*r.

void fasp\_precond\_dbsr\_diag\_nc5 (REAL \*r, REAL \*z, void \*data)

Diagonal preconditioner z=inv(D)\*r.

void fasp\_precond\_dbsr\_diag\_nc7 (REAL \*r, REAL \*z, void \*data)

Diagonal preconditioner z=inv(D)\*r.

void fasp\_precond\_dbsr\_ilu (REAL \*r, REAL \*z, void \*data)

ILU preconditioner.

void fasp\_precond\_dbsr\_amg (REAL \*r, REAL \*z, void \*data)

AMG preconditioner.

void fasp\_precond\_dbsr\_nl\_amli (REAL \*r, REAL \*z, void \*data)

Nonliear AMLI-cycle AMG preconditioner.

# 9.74.1 Detailed Description

Preconditioners for dBSRmat matrices.

Definition in file precond\_bsr.c.

### 9.74.2 Function Documentation

9.74.2.1 void fasp\_precond\_dbsr\_amg ( REAL \* r, REAL \* z, void \* data )

AMG preconditioner.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

**Author** 

Xiaozhe Hu

Date

08/07/2011

Definition at line 561 of file precond\_bsr.c.

9.74.2.2 void fasp\_precond\_dbsr\_diag ( REAL \* r, REAL \* z, void \* data )

Diagonal preconditioner z=inv(D)\*r.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

### **Author**

Zhou Zhiyang, Xiaozhe Hu

Date

10/26/2010

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/24/2012

Note

Works for general nb (Xiaozhe)

Definition at line 35 of file precond\_bsr.c.

9.74.2.3 void fasp\_precond\_dbsr\_diag\_nc2 ( REAL \* r, REAL \* z, void \* data )

Diagonal preconditioner z=inv(D)\*r.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

**Author** 

Zhou Zhiyang, Xiaozhe Hu

Date

11/18/2011

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/24/2012

Note

Works for 2-component (Xiaozhe)

Definition at line 109 of file precond\_bsr.c.

9.74.2.4 void fasp\_precond\_dbsr\_diag\_nc3 ( REAL \* r, REAL \* z, void \* data )

Diagonal preconditioner z=inv(D)\*r.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

# Author

Zhou Zhiyang, Xiaozhe Hu

Date

01/06/2011

Modified by Chunsheng Feng Xiaoqiang Yue

Date

05/24/2012

Note

Works for 3-component (Xiaozhe)

Definition at line 159 of file precond\_bsr.c.

9.74.2.5 void fasp\_precond\_dbsr\_diag\_nc5 ( REAL \* r, REAL \* z, void \* data )

Diagonal preconditioner z=inv(D)\*r.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

**Author** 

Zhou Zhiyang, Xiaozhe Hu

Date

01/06/2011

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/24/2012

Note

Works for 5-component (Xiaozhe)

Definition at line 209 of file precond\_bsr.c.

9.74.2.6 void fasp\_precond\_dbsr\_diag\_nc7 ( REAL \* r, REAL \* z, void \* data )

Diagonal preconditioner z=inv(D)\*r.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Zhou Zhiyang, Xiaozhe Hu

Date

01/06/2011

Modified by Chunsheng Feng Xiaoqiang Yue

Date

05/24/2012

Note

Works for 7-component (Xiaozhe)

Definition at line 258 of file precond\_bsr.c.

9.74.2.7 void fasp\_precond\_dbsr\_ilu ( REAL \* r, REAL \* z, void \* data )

ILU preconditioner.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

# **Author**

Shiquan Zhang

Date

11/09/2010

Note

Works for general nb (Xiaozhe)

Definition at line 304 of file precond\_bsr.c.

9.74.2.8 void fasp\_precond\_dbsr\_nl\_amli ( REAL \* r, REAL \* z, void \* data )

Nonliear AMLI-cycle AMG preconditioner.

#### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

# Author

Xiaozhe Hu

Date

02/06/2012

Definition at line 604 of file precond\_bsr.c.

# 9.75 precond\_csr.c File Reference

Preconditioners for dCSRmat matrices.

```
#include "fasp.h"
#include "fasp_functs.h"
#include "forts_ns.h"
```

### **Functions**

 precond \* fasp\_precond\_setup (SHORT precond\_type, AMG\_param \*amgparam, ILU\_param \*iluparam, dCS-Rmat \*A)

Setup preconditioner interface for iterative methods.

void fasp\_precond\_diag (REAL \*r, REAL \*z, void \*data)

Diagonal preconditioner z=inv(D)\*r.

void fasp\_precond\_ilu (REAL \*r, REAL \*z, void \*data)

ILU preconditioner.

void fasp\_precond\_ilu\_forward (REAL \*r, REAL \*z, void \*data)

ILU preconditioner: only forwear sweep.

void fasp precond ilu backward (REAL \*r, REAL \*z, void \*data)

ILU preconditioner: only backward sweep.

void fasp\_precond\_schwarz (REAL \*r, REAL \*z, void \*data)

get z from r by schwarz

void fasp\_precond\_amg (REAL \*r, REAL \*z, void \*data)

AMG preconditioner.

void fasp\_precond\_famg (REAL \*r, REAL \*z, void \*data)

Full AMG perconditioner.

void fasp\_precond\_amli (REAL \*r, REAL \*z, void \*data)

AMLI AMG preconditioner.

void fasp\_precond\_nl\_amli (REAL \*r, REAL \*z, void \*data)

Nonliear AMLI AMG preconditioner.

void fasp\_precond\_free (SHORT precond\_type, precond \*pc)

free preconditioner

# 9.75.1 Detailed Description

Preconditioners for dCSRmat matrices.

Definition in file precond\_csr.c.

### 9.75.2 Function Documentation

9.75.2.1 void fasp\_precond\_amg ( REAL \* r, REAL \* z, void \* data )

AMG preconditioner.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

# Author

Chensong Zhang

Date

04/06/2010

Definition at line 417 of file precond csr.c.

9.75.2.2 void fasp\_precond\_amli ( REAL \* r, REAL \* z, void \* data )

# AMLI AMG preconditioner.

#### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

### **Author**

Xiaozhe Hu

Date

01/23/2011

Definition at line 488 of file precond\_csr.c.

9.75.2.3 void fasp\_precond\_diag ( REAL \* r, REAL \* z, void \* data )

Diagonal preconditioner z=inv(D)\*r.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

### **Author**

Chensong Zhang

Date

04/06/2010

Definition at line 165 of file precond\_csr.c.

9.75.2.4 void fasp\_precond\_famg ( REAL \* r, REAL \* z, void \* data )

Full AMG perconditioner.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

# **Author**

Xiaozhe Hu

Date

02/27/2011

Definition at line 455 of file precond\_csr.c.

9.75.2.5 void fasp\_precond\_free ( SHORT precond\_type, precond \* pc )

free preconditioner

**Parameters** 

precond_type	Preconditioner type
* <i>pc</i>	precondition data & fct

Returns

void

**Author** 

Feiteng Huang

Date

12/24/2012

Definition at line 557 of file precond\_csr.c.

9.75.2.6 void fasp\_precond\_ilu ( REAL \* r, REAL \* z, void \* data )

ILU preconditioner.

**Parameters** 

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Shiquan Zhang

Date

04/06/2010

Definition at line 191 of file precond\_csr.c.

9.75.2.7 void fasp\_precond\_ilu\_backward ( REAL \* r, REAL \* z, void \* data )

ILU preconditioner: only backward sweep.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

# **Author**

Xiaozhe Hu, Shiquan Zhang

Date

04/06/2010

Definition at line 313 of file precond\_csr.c.

9.75.2.8 void fasp\_precond\_ilu\_forward ( REAL \* r, REAL \* z, void \* data )

ILU preconditioner: only forwear sweep.

#### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

#### **Author**

Xiaozhe Hu, Shiquang Zhang

Date

04/06/2010

Definition at line 260 of file precond\_csr.c.

9.75.2.9 void fasp\_precond\_nl\_amli ( REAL \* r, REAL \* z, void \* data )

Nonliear AMLI AMG preconditioner.

#### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

# Author

Xiaozhe Hu

Date

04/25/2011

Definition at line 521 of file precond\_csr.c.

9.75.2.10 void fasp\_precond\_schwarz ( REAL \* r, REAL \* z, void \* data ) get z from r by schwarz

### **Parameters**

**	pointer to residual
*Z	pointer to preconditioned residual
*data	pointer to precondition data

#### **Author**

Xiaozhe Hu

Date

03/22/2010

Definition at line 363 of file precond\_csr.c.

9.75.2.11 precond \* fasp\_precond\_setup ( SHORT precond\_type, AMG\_param \* amgparam, ILU\_param \* iluparam, dCSRmat \* A )

Setup preconditioner interface for iterative methods.

#### **Parameters**

precond_type	Preconditioner type
*amgparam	AMG parameters
*iluparam	ILU parameters
*A	Pointer to coefficient matrix

#### Returns

Pointer to preconditioner

**Author** 

Feiteng Huang

Date

05/18/2009

Definition at line 30 of file precond\_csr.c.

# 9.76 precond\_str.c File Reference

Preconditioners for dSTRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

### **Functions**

void fasp\_precond\_dstr\_diag (REAL \*r, REAL \*z, void \*data)

Diagonal preconditioner z=inv(D)\*r.

void fasp\_precond\_dstr\_ilu0 (REAL \*r, REAL \*z, void \*data)

Preconditioning using STR\_ILU(0) decomposition.

void fasp\_precond\_dstr\_ilu1 (REAL \*r, REAL \*z, void \*data)

Preconditioning using STR\_ILU(1) decomposition.

void fasp\_precond\_dstr\_ilu0\_forward (REAL \*r, REAL \*z, void \*data)

Preconditioning using  $STR_ILU(0)$  decomposition: Lz = r.

void fasp\_precond\_dstr\_ilu0\_backward (REAL \*r, REAL \*z, void \*data)

Preconditioning using  $STR_ILU(0)$  decomposition: Uz = r.

void fasp precond dstr ilu1 forward (REAL \*r, REAL \*z, void \*data)

Preconditioning using  $STR_ILU(1)$  decomposition: Lz = r.

void fasp precond dstr ilu1 backward (REAL \*r, REAL \*z, void \*data)

Preconditioning using STR\_ILU(1) decomposition: Uz = r.

void fasp\_precond\_dstr\_blockgs (REAL \*r, REAL \*z, void \*data)

CPR-type preconditioner (STR format)

# 9.76.1 Detailed Description

Preconditioners for dSTRmat matrices.

Definition in file precond str.c.

# 9.76.2 Function Documentation

9.76.2.1 void fasp\_precond\_dstr\_blockgs ( REAL \* r, REAL \* z, void \* data )

CPR-type preconditioner (STR format)

#### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

### Author

Shiquan Zhang

Date

10/17/2010

Definition at line 1707 of file precond\_str.c.

9.76.2.2 void fasp\_precond\_dstr\_diag ( REAL \* r, REAL \* z, void \* data )

Diagonal preconditioner z=inv(D)\*r.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

# Author

Shiquan Zhang

Date

04/06/2010

Definition at line 27 of file precond\_str.c.

9.76.2.3 void fasp\_precond\_dstr\_ilu0 ( REAL \* r, REAL \* z, void \* data )

Preconditioning using STR\_ILU(0) decomposition.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

#### **Author**

Shiquan Zhang

Date

04/21/2010

Definition at line 55 of file precond str.c.

9.76.2.4 void fasp\_precond\_dstr\_ilu0\_backward ( REAL \* r, REAL \* z, void \* data )

Preconditioning using  $STR_ILU(0)$  decomposition: Uz = r.

### **Parameters**

	r	Pointer to the vector needs preconditioning
	Z	Pointer to preconditioned vector
da	ata	Pointer to precondition data

### **Author**

Shiquan Zhang

Date

06/07/2010

Definition at line 979 of file precond\_str.c.

9.76.2.5 void fasp\_precond\_dstr\_ilu0\_forward ( REAL \* r, REAL \* z, void \* data )

Preconditioning using  $STR_ILU(0)$  decomposition: Lz = r.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

# Author

Shiquan Zhang

Date

06/07/2010

Definition at line 816 of file precond\_str.c.

9.76.2.6 void fasp\_precond\_dstr\_ilu1 ( REAL \* r, REAL \* z, void \* data )

Preconditioning using STR\_ILU(1) decomposition.

### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

#### **Author**

Shiquan Zhang

Date

04/21/2010

Definition at line 337 of file precond str.c.

9.76.2.7 void fasp\_precond\_dstr\_ilu1\_backward ( REAL \* r, REAL \* z, void \* data )

Preconditioning using  $STR_ILU(1)$  decomposition: Uz = r.

### **Parameters**

	r	Pointer to the vector needs preconditioning
	Z	Pointer to preconditioned vector
ĺ	data	Pointer to precondition data

### **Author**

Shiquan Zhang

Date

04/21/2010

Definition at line 1426 of file precond\_str.c.

9.76.2.8 void fasp\_precond\_dstr\_ilu1\_forward ( REAL \* r, REAL \* z, void \* data )

Preconditioning using  $STR_ILU(1)$  decomposition: Lz = r.

#### **Parameters**

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

#### **Author**

Shiquan Zhang

Date

04/21/2010

Definition at line 1160 of file precond str.c.

# 9.77 pvfgmres.c File Reference

Krylov subspace methods – Preconditioned variable-restarting flexible GMRes.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

# **Functions**

 INT fasp\_solver\_dcsr\_pvfgmres (dCSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Solve "Ax=b" using PFGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration and flexible preconditioner can be used.

 INT fasp\_solver\_dbsr\_pvfgmres (dBSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Solve "Ax=b" using PFGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration and flexible preconditioner can be used.

# 9.77.1 Detailed Description

Krylov subspace methods – Preconditioned variable-restarting flexible GMRes.

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM
Refer to A.H. Baker, E.R. Jessup, and Tz.V. Kolev A Simple Strategy for Varying the Restart Parameter in GMRE-S(m) Journal of Computational and Applied Mathematics, 230 (2009) pp. 751-761. UCRL-JRNL-235266.
This file is modifed from pvgmres.c

Definition in file pvfgmres.c.

# 9.77.2 Function Documentation

9.77.2.1 INT fasp\_solver\_dbsr\_pvfgmres ( dBSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Solve "Ax=b" using PFGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration and flexible preconditioner can be used.

### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type – DOES not support this parameter
print_level	How much information to print out

### Returns

Number of iterations if converged, error message otherwise

#### **Author**

Xiaozhe Hu

Date

02/05/2012

Modified by Chensong Zhang on 05/01/2012

Definition at line 371 of file pvfgmres.c.

9.77.2.2 INT fasp\_solver\_dcsr\_pvfgmres ( dCSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Solve "Ax=b" using PFGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration and flexible preconditioner can be used.

### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type – DOES not support this parameter
print_level	How much information to print out

# Returns

Number of iterations if converged, error message otherwise

#### Author

Xiaozhe Hu

Date

01/04/2012

Modified by Chensong Zhang on 05/01/2012 Modified by Chunsheng Feng on 07/22/2013: Add adaptive memory allocate

Definition at line 54 of file pvfgmres.c.

# 9.78 pvfgmres\_mf.c File Reference

Krylov subspace methods – Preconditioned variable-restarting flexible GMRes (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

#### **Functions**

 INT fasp\_solver\_pvfgmres (mxv\_matfree \*mf, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop type, const SHORT print level)

Solve "Ax=b" using PFGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration and flexible preconditioner can be used.

# 9.78.1 Detailed Description

Krylov subspace methods - Preconditioned variable-restarting flexible GMRes (matrix free)

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM Refer to A.H. Baker, E.R. Jessup, and Tz.V. Kolev A Simple Strategy for Varying the Restart Parameter in GMRE-S(m) Journal of Computational and Applied Mathematics, 230 (2009) pp. 751-761. UCRL-JRNL-235266. This file is modifed from pvgmres.c

Definition in file pvfgmres\_mf.c.

### 9.78.2 Function Documentation

9.78.2.1 INT fasp\_solver\_pvfgmres ( mxv\_matfree \* mf, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Solve "Ax=b" using PFGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration and flexible preconditioner can be used.

#### **Parameters**

Pointer to mxv_matfree: the spmv operation
Pointer to dvector: the right hand side
Pointer to dvector: the unknowns
Pointer to precond: the structure of precondition
Tolerance for stopping
Maximal number of iterations
Restarting steps
Stopping criteria type – DOES not support this parameter
How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

#### **Author**

Xiaozhe Hu

#### Date

01/04/2012

Modified by Chensong Zhang on 05/01/2012 Modified by Feiteng Huang on 09/26/2012, (matrix free) Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate

Definition at line 56 of file pyfgmres mf.c.

# 9.79 pygmres.c File Reference

Krylov subspace methods – Preconditioned variable-restart GMRes.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

### **Functions**

 INT fasp\_solver\_dcsr\_pvgmres (dCSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

• INT fasp\_solver\_bdcsr\_pvgmres (block\_dCSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop type, const SHORT print level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

 INT fasp\_solver\_dbsr\_pvgmres (dBSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level) Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

 INT fasp\_solver\_dstr\_pvgmres (dSTRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

# 9.79.1 Detailed Description

Krylov subspace methods - Preconditioned variable-restart GMRes.

Note

Refer to A.H. Baker, E.R. Jessup, and Tz.V. Kolev A Simple Strategy for Varying the Restart Parameter in GMRE-S(m) Journal of Computational and Applied Mathematics, 230 (2009) pp. 751-761. UCRL-JRNL-235266. See spvgmres.c for a safer version

Definition in file pvgmres.c.

#### 9.79.2 Function Documentation

9.79.2.1 INT fasp\_solver\_bdcsr\_pvgmres ( block\_dCSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

**Author** 

Chensong Zhang

Date

04/05/2013

Definition at line 384 of file pygmres.c.

9.79.2.2 INT fasp\_solver\_dbsr\_pvgmres ( dBSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

### **Author**

Zhiyang Zhou

Date

12/21/2011

Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/06/2013: Add stop type support Definition at line 719 of file pygmres.c.

9.79.2.3 INT fasp\_solver\_dcsr\_pvgmres ( dCSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

# Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
Х	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

### Returns

Number of iterations if converged, error message otherwise

# **Author**

Zhiyang Zhou

Date

2010/12/14

Modified by Chensong Zhang on 12/13/2011 Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/06/2013: Add stop type support Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate Definition at line 52 of file pygmres.c.

9.79.2.4 INT fasp\_solver\_dstr\_pvgmres ( dSTRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

#### Author

Zhiyang Zhou

Date

2010/12/14

Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/06/2013: Add stop type support Definition at line 1054 of file pygmres.c.

# 9.80 pvgmres\_mf.c File Reference

Krylov subspace methods – Preconditioned variable-restarting GMRes (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

#### **Functions**

 INT fasp\_solver\_pvgmres (mxv\_matfree \*mf, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

#### 9.80.1 Detailed Description

Krylov subspace methods – Preconditioned variable-restarting GMRes (matrix free)

Note

Refer to A.H. Baker, E.R. Jessup, and Tz.V. Kolev A Simple Strategy for Varying the Restart Parameter in GMRE-S(m) Journal of Computational and Applied Mathematics, 230 (2009) pp. 751-761. UCRL-JRNL-235266.

Definition in file pvgmres\_mf.c.

#### 9.80.2 Function Documentation

9.80.2.1 INT fasp\_solver\_pvgmres ( mxv\_matfree \* mf, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

#### **Parameters**

mf	Pointer to mxv_matfree: the spmv operation
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type – DOES not support this parameter
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

# **Author**

Zhiyang Zhou

Date

2010/12/14

Modified by Chensong Zhang on 12/13/2011 Modified by Chensong Zhang on 05/01/2012 Modified by Feiteng Huang on 09/26/2012, (matrix free) Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate

Definition at line 54 of file pygmres mf.c.

# 9.81 quadrature.c File Reference

#### Quadrature rules.

```
#include <stdio.h>
#include "fasp.h"
#include "fasp_functs.h"
```

# **Functions**

void fasp\_quad2d (INT num\_qp, INT ncoor, REAL(\*quad)[3])

Initialize Lagrange quadrature points and weights.

• void fasp\_gauss2d (INT num\_qp, INT ncoor, REAL(\*gauss)[3])

Initialize Gauss quadrature points and weights.

# 9.81.1 Detailed Description

Quadrature rules.

Definition in file quadrature.c.

### 9.81.2 Function Documentation

9.81.2.1 void fasp\_gauss2d ( INT num\_qp, INT ncoor, REAL(\*) gauss[3] )

Initialize Gauss quadrature points and weights.

#### **Parameters**

	num_qp	Number of quadrature points
	ncoor	Dimension of space
ſ	gauss	Quadrature points and weight

### **Author**

Xuehai Huang, Chensong Zhang, Ludmil Zikatanov

Date

10/21/2008

Note

gauss[\*][0] - quad point x in ref coor <math>gauss[\*][1] - quad point y in ref coor <math>gauss[\*][2] - quad weight

Definition at line 210 of file quadrature.c.

9.81.2.2 void fasp\_quad2d ( INT num\_qp, INT ncoor, REAL(\*) quad[3] )

Initialize Lagrange quadrature points and weights.

### **Parameters**

num_qp	Number of quadrature points
ncoor	Dimension of space
quad	Quadrature points and weights

#### **Author**

Xuehai Huang, Chensong Zhang, Ludmil Zikatanov

Date

10/21/2008

Note

quad[\*][0] - quad point x in ref coor quad[\*][1] - quad point y in ref coor quad[\*][2] - quad weight

Definition at line 31 of file quadrature.c.

# 9.82 rap.c File Reference

### R\*A\*P driver.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

### **Functions**

```
    dCSRmat fasp_blas_dcsr_rap2 (INT *ir, INT *jr, REAL *r, INT *ia, INT *ja, REAL *a, INT *ipt, INT *jpt, REAL *pt, INT n, INT nc, INT *maxrpout, INT *ipin, INT *jpin)
    Compute R*A*P.
```

# 9.82.1 Detailed Description

R\*A\*P driver.

C-version by Ludmil Zikatanov 2010-04-08

tested 2010-04-08

Definition in file rap.c.

### 9.82.2 Function Documentation

```
9.82.2.1 dCSRmat fasp_blas_dcsr_rap2 ( INT * ir, INT * jr, REAL * r, INT * ia, INT * ja, REAL * a, INT * ipt, INT * jpt, REAL * pt, INT n, INT nc, INT * maxrpout, INT * ipin, INT * jpin )
```

Compute R\*A\*P.

**Author** 

Ludmil Zikatanov

Date

04/08/2010

Note

It uses dCSRmat only. The functions called from here are in sparse util.c

Definition at line 33 of file rap.c.

# 9.83 schwarz.f File Reference

Schwarz smoothers.

#### **Functions/Subroutines**

- subroutine cut0 (n, ia, ja, a, iaw, jaw, jblk, iblk, nblk, lwork1, lwork2, lwork3, msize)
- subroutine chsize (a, b, tol, imin)
- subroutine **shift** (nxadj, nadj, n)
- subroutine dfs (n, ia, ja, nblk, iblk, jblk, lowlink, iedge, numb)
- subroutine **permat** (iord, ia, ja, an, n, m, iat, jat, ant)
- subroutine pervec (iord, u1, u2, n)
- subroutine **perback** (iord, u1, u2, n)
- subroutine **perm0** (iord, ia, ja, an, n, m, iat, jat, ant)
- subroutine icopyv (iu, iv, n)
- subroutine mxfrm2 (n, ia, ja, nblk, iblock, jblock, mask, maxa, memt, maxbs)
- subroutine **sky2ns** (n, ia, ja, a, nblk, iblock, jblock, mask, maxa, au, al)
- subroutine **fbgs2ns** (n, ia, ja, a, x, b, nblk, iblock, jblock, mask, maxa, au, al, rhsloc, memt)
- subroutine **bbgs2ns** (n, ia, ja, a, x, b, nblk, iblock, jblock, mask, maxa, au, al, rhsloc, memt)
- subroutine doluns (au, al, maxa, nn)
- subroutine **sluns** (au, al, v, maxa, nn)
- subroutine dolu (a, maxa, nn)
- subroutine siviu (a, v, maxa, nn)
- subroutine ijacrs (In, ia, ja, a, n, nnz, ir, ic, aij)
- subroutine sympat (In, ia, ja, n, ir, ic, aij)
- subroutine levels (inroot, ia, ja, mask, nlvl, iblock, jblock, maxlev)

### 9.83.1 Detailed Description

Schwarz smoothers.

**Author** 

Ludmil Zikatanov

Date

01/01/2007

Note

These routines are part of the matching MG method

Definition in file schwarz.f.

# 9.84 schwarz\_setup.c File Reference

Setup phase for the Schwarz methods.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "forts_ns.h"
```

# **Functions**

INT fasp\_schwarz\_setup (Schwarz\_data \*schwarz, INT mmsize, INT maxlev, INT schwarz\_type)
 Setup phase for the Schwarz methods.

# 9.84.1 Detailed Description

Setup phase for the Schwarz methods.

Definition in file schwarz\_setup.c.

### 9.84.2 Function Documentation

9.84.2.1 INT fasp\_schwarz\_setup ( Schwarz\_data \* schwarz, INT mmsize, INT maxlev, INT schwarz\_type )

Setup phase for the Schwarz methods.

#### **Parameters**

Г	schwarz	Pointer to the showarz data
	mmsize	Max block size
	maxlev	Max number of levels
	schwarz_type	Type of the Schwarz method

# Returns

SUCCESS if succeed

```
Author
```

Ludmil, Xiaozhe Hu

Date

03/22/2011

Modified by Chunsheng Feng, Zheng Li on 08/28/2012 find the blocks

LU decomposition of blocks

return

Definition at line 35 of file schwarz\_setup.c.

# 9.85 smat.c File Reference

Simple operations for *small* full matrices in row-major format.

```
#include "fasp.h"
#include "fasp_functs.h"
```

### **Functions**

void fasp blas smat inv nc2 (REAL \*a)

Compute the inverse matrix of a 2\*2 full matrix A (in place)

void fasp\_blas\_smat\_inv\_nc3 (REAL \*a)

Compute the inverse matrix of a 3\*3 full matrix A (in place)

void fasp\_blas\_smat\_inv\_nc4 (REAL \*a)

Compute the inverse matrix of a 4\*4 full matrix A (in place)

void fasp\_blas\_smat\_inv\_nc5 (REAL \*a)

Compute the inverse matrix of a 5\*5 full matrix A (in place)

void fasp\_blas\_smat\_inv\_nc7 (REAL \*a)

Compute the inverse matrix of a 7\*7 matrix a.

INT fasp\_blas\_smat\_inv (REAL \*a, const INT n)

Compute the inverse matrix of a small full matrix a.

void fasp\_iden\_free (idenmat \*A)

Free idenmat sparse matrix data memeory space.

void fasp\_smat\_identity\_nc2 (REAL \*a)

Set a 2\*2 full matrix to be a identity.

• void fasp\_smat\_identity\_nc3 (REAL \*a)

Set a 3\*3 full matrix to be a identity.

void fasp\_smat\_identity\_nc5 (REAL \*a)

Set a 5\*5 full matrix to be a identity.

void fasp\_smat\_identity\_nc7 (REAL \*a)

Set a 7\*7 full matrix to be a identity.

void fasp\_smat\_identity (REAL \*a, INT n, INT n2)

Set a n\*n full matrix to be a identity.

9.85 smat.c File Reference 325

### 9.85.1 Detailed Description

Simple operations for small full matrices in row-major format.

Definition in file smat.c.

### 9.85.2 Function Documentation

9.85.2.1 INT fasp\_blas\_smat\_inv ( REAL \* a, const INT n )

Compute the inverse matrix of a small full matrix a.

#### **Parameters**

а	Pointer to the REAL array which stands a n∗n matrix
n	Dimension of the matrix

#### **Author**

Xiaozhe Hu, Shiquan Zhang

Date

04/21/2010

Definition at line 392 of file smat.c.

9.85.2.2 void fasp\_blas\_smat\_inv\_nc2 ( REAL \* a )

Compute the inverse matrix of a 2\*2 full matrix A (in place)

**Parameters** 

а	Pointer to the REAL array which stands a 2*2 matrix

**Author** 

Xiaozhe Hu

Date

18/11/2011

Definition at line 23 of file smat.c.

9.85.2.3 void fasp\_blas\_smat\_inv\_nc3 ( REAL \* a )

Compute the inverse matrix of a 3\*3 full matrix A (in place)

**Parameters** 

a Pointer to the REAL array which stands a 3\*3 matrix

**Author** 

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 59 of file smat.c.

9.85.2.4 void fasp\_blas\_smat\_inv\_nc4 ( REAL \* a )

Compute the inverse matrix of a 4\*4 full matrix A (in place)

**Parameters** 

a Pointer to the REAL array which stands a 4\*4 matrix

**Author** 

Xiaozhe Hu

Date

01/12/2013

Definition at line 102 of file smat.c.

9.85.2.5 void fasp\_blas\_smat\_inv\_nc5 ( REAL \* a )

Compute the inverse matrix of a 5\*5 full matrix A (in place)

**Parameters** 

a Pointer to the REAL array which stands a 5\*5 matrix

**Author** 

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 160 of file smat.c.

9.85.2.6 void fasp\_blas\_smat\_inv\_nc7 ( REAL \* a )

Compute the inverse matrix of a 7\*7 matrix a.

9.85 smat.c File Reference 327

#### **Parameters**

a Pointer to the REAL array which stands a 7*7 matrix		
	а	Pointer to the REAL array which stands a 7*7 matrix

Note

This is NOT implemented yet!

**Author** 

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 376 of file smat.c.

9.85.2.7 void fasp\_iden\_free ( idenmat \* A )

Free idenmat sparse matrix data memeory space.

**Parameters** 

Α	Pointer to the idenmat matrix
---	-------------------------------

**Author** 

Chensong Zhang

Date

2010/04/03

Definition at line 481 of file smat.c.

9.85.2.8 void fasp\_smat\_identity ( REAL \* a, INT n, INT n2 )

Set a n\*n full matrix to be a identity.

#### **Parameters**

а	Pointer to the REAL vector which stands for a n∗n full matrix
n	Size of full matrix
n2	Length of the REAL vector which stores the n∗n full matrix

Author

Xiaozhe Hu

Date

2010/12/25

Definition at line 581 of file smat.c.

9.85.2.9 void fasp\_smat\_identity\_nc2 ( REAL \*a )

Set a 2\*2 full matrix to be a identity.

9.85 smat.c File Reference 329

**Parameters** 

a Pointer to the REAL vector which stands for a 2\*2 full matrix

**Author** 

Xiaozhe Hu

Date

2011/11/18

Definition at line 501 of file smat.c.

9.85.2.10 void fasp\_smat\_identity\_nc3 ( REAL \* a )

Set a 3\*3 full matrix to be a identity.

**Parameters** 

a Pointer to the REAL vector which stands for a 3\*3 full matrix

**Author** 

Xiaozhe Hu

Date

2010/12/25

Definition at line 518 of file smat.c.

9.85.2.11 void fasp\_smat\_identity\_nc5 ( REAL \*a )

Set a 5\*5 full matrix to be a identity.

**Parameters** 

a Pointer to the REAL vector which stands for a 5∗5 full matrix

**Author** 

Xiaozhe Hu

Date

2010/12/25

Definition at line 535 of file smat.c.

9.85.2.12 void fasp\_smat\_identity\_nc7 ( REAL \*a )

Set a 7\*7 full matrix to be a identity.

#### **Parameters**

a Pointer to the REAL vector which stands for a 7\*7 full matrix

Author

Xiaozhe Hu

Date

2010/12/25

Definition at line 556 of file smat.c.

### 9.86 smoother bsr.c File Reference

Smoothers for dBSRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

- void fasp\_smoother\_dbsr\_jacobi (dBSRmat \*A, dvector \*b, dvector \*u)
   Jacobi relaxation.
- void fasp\_smoother\_dbsr\_jacobi\_setup (dBSRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv)

  Setup for jacobi relaxation, fetch the diagonal sub-block matrixes and make them inverse first.
- void fasp\_smoother\_dbsr\_jacobi1 (dBSRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv)
   Jacobi relaxation.
- void fasp\_smoother\_dbsr\_gs (dBSRmat \*A, dvector \*b, dvector \*u, INT order, INT \*mark)
   Gauss-Seidel relaxation.
- void fasp\_smoother\_dbsr\_gs1 (dBSRmat \*A, dvector \*b, dvector \*u, INT order, INT \*mark, REAL \*diaginv) Gauss-Seidel relaxation.
- $\bullet \ \ void \ fasp\_smoother\_dbsr\_gs\_ascend \ (dBSRmat \ *A, \ dvector \ *b, \ dvector \ *u, \ REAL \ *diaginv)$
- Gauss-Seidel relaxation in the ascending order.
   void fasp\_smoother\_dbsr\_gs\_descend (dBSRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv)
- void fasp\_smoother\_dbsr\_gs\_descend (dBSRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv)
   Gauss-Seidel relaxation in the descending order.
- void fasp\_smoother\_dbsr\_gs\_order1 (dBSRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv, INT \*mark)
   Gauss-Seidel relaxation in the user-defined order.
- void fasp\_smoother\_dbsr\_gs\_order2 (dBSRmat \*A, dvector \*b, dvector \*u, INT \*mark, REAL \*work)

  Gauss-Seidel relaxation in the user-defined order.
- void fasp\_smoother\_dbsr\_sor (dBSRmat \*A, dvector \*b, dvector \*u, INT order, INT \*mark, REAL weight) SOR relaxation.
- void fasp\_smoother\_dbsr\_sor1 (dBSRmat \*A, dvector \*b, dvector \*u, INT order, INT \*mark, REAL \*diaginv, REAL weight)

SOR relaxation.

void fasp smoother dbsr sor ascend (dBSRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv, REAL weight)

SOR relaxation in the ascending order.

- void fasp\_smoother\_dbsr\_sor\_descend (dBSRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv, REAL weight) SOR relaxation in the descending order.
- void fasp\_smoother\_dbsr\_sor\_order (dBSRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv, INT \*mark, REAL weight)

SOR relaxation in the user-defined order.

• void fasp\_smoother\_dbsr\_ilu (dBSRmat \*A, dvector \*b, dvector \*x, void \*data)

ILU method as the smoother in solving Au=b with multigrid method.

### 9.86.1 Detailed Description

Smoothers for dBSRmat matrices.

Definition in file smoother bsr.c.

#### 9.86.2 Function Documentation

9.86.2.1 void fasp\_smoother\_dbsr\_gs ( dBSRmat \* A, dvector \* b, dvector \* u, INT order, INT \* mark )

Gauss-Seidel relaxation.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending order DES-
	CEND 21: in descending order If mark != NULL: in the user-defined order
mark	Pointer to NULL or to the user-defined ordering

#### **Author**

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 08/03/2012

Definition at line 415 of file smoother\_bsr.c.

9.86.2.2 void fasp\_smoother\_dbsr\_gs1 ( dBSRmat \* A, dvector \* b, dvector \* u, INT order, INT \* mark, REAL \* diaginv )

Gauss-Seidel relaxation.

**Parameters** 

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending order DES-
	CEND 21: in descending order If mark != NULL: in the user-defined order
mark	Pointer to NULL or to the user-defined ordering
diaginv	Inverses for all the diagonal blocks of A

### Author

Zhiyang Zhou

Date

2010/10/25

Definition at line 535 of file smoother\_bsr.c.

9.86.2.3 void fasp\_smoother\_dbsr\_gs\_ascend ( dBSRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv )

Gauss-Seidel relaxation in the ascending order.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
diaginv	Inverses for all the diagonal blocks of A

### Author

Zhiyang Zhou

Date

2010/10/25

Definition at line 572 of file smoother\_bsr.c.

9.86.2.4 void fasp\_smoother\_dbsr\_gs\_descend ( dBSRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv )

Gauss-Seidel relaxation in the descending order.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)

diaginv	Inverses for all the diagonal blocks of A
---------	---

**Author** 

Zhiyang Zhou

Date

2010/10/25

Definition at line 642 of file smoother\_bsr.c.

9.86.2.5 void fasp\_smoother\_dbsr\_gs\_order1 ( dBSRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv, INT \* mark )

Gauss-Seidel relaxation in the user-defined order.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
diaginv	Inverses for all the diagonal blocks of A
mark	Pointer to the user-defined ordering

**Author** 

Zhiyang Zhou

Date

2010/10/25

Definition at line 713 of file smoother\_bsr.c.

9.86.2.6 void fasp\_smoother\_dbsr\_gs\_order2 ( dBSRmat \* A, dvector \* b, dvector \* u, INT \* mark, REAL \* work )

Gauss-Seidel relaxation in the user-defined order.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
mark	Pointer to the user-defined ordering
work	Work temp array

**Author** 

Zhiyang Zhou

Date

2010/11/08

Note

The only difference between the functions 'fasp\_smoother\_dbsr\_gs\_order2' and 'fasp\_smoother\_dbsr\_gs\_order1' lies in that we don't have to multiply by the inverses of the diagonal blocks in each ROW since matrix A has been such scaled that all the diagonal blocks become identity matrices.

Definition at line 791 of file smoother\_bsr.c.

```
9.86.2.7 void fasp_smoother_dbsr_ilu ( dBSRmat * A, dvector * b, dvector * x, void * data )
```

ILU method as the smoother in solving Au=b with multigrid method.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
data	Pointer to user defined data

#### **Author**

Zhiyang Zhou

Date

2010/10/25

form residual zr = b - A x

solve LU z=zr

X=X+Z

Definition at line 1424 of file smoother\_bsr.c.

9.86.2.8 void fasp\_smoother\_dbsr\_jacobi ( dBSRmat \* A, dvector \* b, dvector \* u )

Jacobi relaxation.

### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)

### Author

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 08/02/2012

Definition at line 35 of file smoother\_bsr.c.

9.86.2.9 void fasp\_smoother\_dbsr\_jacobi1 ( dBSRmat\*A, dvector\*b, dvector\*u, REAL\*diaginv ) Jacobi relaxation.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
diaginv	Inverses for all the diagonal blocks of A

#### **Author**

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 08/03/2012

Definition at line 259 of file smoother\_bsr.c.

9.86.2.10 void fasp\_smoother\_dbsr\_jacobi\_setup ( dBSRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv )

Setup for jacobi relaxation, fetch the diagonal sub-block matrixes and make them inverse first.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
diaginv	Inverse of the diagonal entries

### Author

Zhiyang Zhou

Date

10/25/2010

Modified by Chunsheng Feng, Zheng Li on 08/02/2012

Definition at line 150 of file smoother\_bsr.c.

9.86.2.11 void fasp\_smoother\_dbsr\_sor ( dBSRmat \* A, dvector \* b, dvector \* u, INT order, INT \* mark, REAL weight )

SOR relaxation.

### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side

и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending order DES-
	CEND 21: in descending order If mark != NULL: in the user-defined order
mark	Pointer to NULL or to the user-defined ordering
weight	Over-relaxation weight

**Author** 

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 08/03/2012

Definition at line 870 of file smoother\_bsr.c.

9.86.2.12 void fasp\_smoother\_dbsr\_sor1 ( dBSRmat \* A, dvector \* b, dvector \* u, INT order, INT \* mark, REAL \* diaginv, REAL weight )

#### SOR relaxation.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending order DES-
	CEND 21: in descending order If mark != NULL: in the user-defined order
mark	Pointer to NULL or to the user-defined ordering
diaginv	Inverses for all the diagonal blocks of A
weight	Over-relaxation weight

#### **Author**

Zhiyang Zhou

Date

2010/10/25

Definition at line 992 of file smoother\_bsr.c.

9.86.2.13 void fasp\_smoother\_dbsr\_sor\_ascend ( dBSRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv, REAL weight )

SOR relaxation in the ascending order.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
diaginv	Inverses for all the diagonal blocks of A
weight	Over-relaxation weight

### **Author**

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 2012/09/04

Definition at line 1033 of file smoother\_bsr.c.

9.86.2.14 void fasp\_smoother\_dbsr\_sor\_descend ( dBSRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv, REAL weight )

SOR relaxation in the descending order.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
diaginv	Inverses for all the diagonal blocks of A
weight	Over-relaxation weight

### Author

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 2012/09/04

Definition at line 1162 of file smoother\_bsr.c.

9.86.2.15 void fasp\_smoother\_dbsr\_sor\_order ( dBSRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv, INT \* mark, REAL weight )

SOR relaxation in the user-defined order.

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
diaginv	Inverses for all the diagonal blocks of A
mark	Pointer to the user-defined ordering
weight	Over-relaxation weight

#### Author

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 2012/09/04

Definition at line 1293 of file smoother\_bsr.c.

## 9.87 smoother csr.c File Reference

Smoothers for dCSRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

void fasp\_smoother\_dcsr\_jacobi (dvector \*u, const INT i\_1, const INT i\_n, const INT s, dCSRmat \*A, dvector \*b, INT L)

Jacobi method as a smoother.

void fasp\_smoother\_dcsr\_gs (dvector \*u, const INT i\_1, const INT i\_n, const INT s, dCSRmat \*A, dvector \*b, INT L)

Gauss-Seidel method as a smoother.

- void fasp\_smoother\_dcsr\_gs\_cf (dvector \*u, dCSRmat \*A, dvector \*b, INT L, INT \*mark, const INT order)

  Gauss-Seidel smoother with C/F ordering for Au=b.
- void fasp\_smoother\_dcsr\_sgs (dvector \*u, dCSRmat \*A, dvector \*b, INT L)

Symmetric Gauss-Seidel method as a smoother.

void fasp\_smoother\_dcsr\_sor (dvector \*u, const INT i\_1, const INT i\_n, const INT s, dCSRmat \*A, dvector \*b, INT L, const REAL w)

SOR method as a smoother.

void fasp\_smoother\_dcsr\_sor\_cf (dvector \*u, dCSRmat \*A, dvector \*b, INT L, const REAL w, INT \*mark, const INT order)

SOR smoother with C/F ordering for Au=b.

void fasp\_smoother\_dcsr\_ilu (dCSRmat \*A, dvector \*b, dvector \*x, void \*data)

ILU method as a smoother.

void fasp\_smoother\_dcsr\_kaczmarz (dvector \*u, const INT i\_1, const INT i\_n, const INT s, dCSRmat \*A, dvector \*b, INT L, const REAL w)

Kaczmarz method as a smoother.

void fasp\_smoother\_dcsr\_L1diag (dvector \*u, const INT i\_1, const INT i\_n, const INT s, dCSRmat \*A, dvector \*b, INT L)

Diagonal scaling (using L1 norm) as a smoother.

void fasp\_smoother\_dcsr\_gs\_rb3d (dvector \*u, dCSRmat \*A, dvector \*b, INT L, INT order, INT \*mark, INT maximap, INT nx, INT ny, INT nz)

### 9.87.1 Detailed Description

Smoothers for dCSRmat matrices.

Definition in file smoother\_csr.c.

### 9.87.2 Function Documentation

9.87.2.1 void fasp\_smoother\_dcsr\_gs ( dvector \*u, const INT i\_1, const INT i\_n, const INT s, dCSRmat \*A, dvector \*b, INT L)

Gauss-Seidel method as a smoother.

#### **Parameters**

И	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
<u>i_1</u>	Starting index
i_n	Ending index
s	Increasing step
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations

#### **Author**

Xuehai Huang, Chensong Zhang

Date

09/26/2009

Modified by Chunsheng Feng, Zheng Li on 09/01/2012

Definition at line 195 of file smoother\_csr.c.

9.87.2.2 void fasp\_smoother\_dcsr\_gs\_cf ( dvector \* u, dCSRmat \* A, dvector \* b, INT L, INT \* mark, const INT order )

Gauss-Seidel smoother with C/F ordering for Au=b.

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations
mark	C/F marker array
order	C/F ordering: -1: F-first; 1: C-first

#### **Author**

Zhiyang Zhou

Date

11/12/2010

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/24/2012

Definition at line 364 of file smoother\_csr.c.

9.87.2.3 void fasp\_smoother\_dcsr\_ilu ( dCSRmat \* A, dvector \* b, dvector \* x, void \* data )

ILU method as a smoother.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
Χ	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
data	Pointer to user defined data

#### **Author**

Shiquan Zhang, Xiaozhe Hu

Date

2010/11/12

form residual zr = b - Ax

Definition at line 1067 of file smoother\_csr.c.

9.87.2.4 void fasp\_smoother\_dcsr\_jacobi ( dvector \* u, const INT i\_1, const INT i\_n, const INT s, dCSRmat \* A, dvector \* b, INT L )

Jacobi method as a smoother.

#### **Parameters**

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
<u>i_1</u>	Starting index
<u>i_</u> n	Ending index
S	Increasing step
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations

#### **Author**

Xuehai Huang, Chensong Zhang

Date

09/26/2009

Modified by Chunsheng Feng, Zheng Li on 08/29/2012

Definition at line 59 of file smoother\_csr.c.

9.87.2.5 void fasp\_smoother\_dcsr\_kaczmarz ( dvector \*u, const INT i\_1, const INT i\_n, const INT s, dCSRmat \*A, dvector \*b, INT L, const REAL w)

Kaczmarz method as a smoother.

### **Parameters**

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
<u>i_1</u>	Starting index
i_n	Ending index
S	Increasing step
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations
W	Over-relaxation weight

### Author

Xiaozhe Hu

Date

2010/11/12

Modified by Chunsheng Feng, Zheng Li on 2012/09/01

Definition at line 1144 of file smoother\_csr.c.

9.87.2.6 void fasp\_smoother\_dcsr\_L1diag ( dvector \*u, const INT i\_1, const INT i\_n, const INT s, dCSRmat \*A, dvector \*b, INT L)

Diagonal scaling (using L1 norm) as a smoother.

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
<u>i_1</u>	Starting index
<u>i_</u> n	Ending index
S	Increasing step
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations

#### Author

Xiaozhe Hu, James Brannick

Date

01/26/2011

Modified by Chunsheng Feng, Zheng Li on 09/01/2012

Definition at line 1285 of file smoother\_csr.c.

9.87.2.7 void fasp\_smoother\_dcsr\_sgs ( dvector \* u, dCSRmat \* A, dvector \* b, INT L )

Symmetric Gauss-Seidel method as a smoother.

#### **Parameters**

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations

#### **Author**

Xiaozhe Hu

Date

10/26/2010

Modified by Chunsheng Feng, Zheng Li on 09/01/2012

Definition at line 629 of file smoother\_csr.c.

9.87.2.8 void fasp\_smoother\_dcsr\_sor ( dvector \*u, const INT i\_1, const INT i\_n, const INT s, dCSRmat \*A, dvector \*b, INT L, const REAL w)

SOR method as a smoother.

#### **Parameters**

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
<u>i_1</u>	Starting index
i_n	Ending index
S	Increasing step
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations
W	Over-relaxation weight

#### **Author**

Xiaozhe Hu

Date

10/26/2010

Modified by Chunsheng Feng, Zheng Li on 09/01/2012

Definition at line 745 of file smoother\_csr.c.

9.87.2.9 void fasp\_smoother\_dcsr\_sor\_cf ( dvector \* u, dCSRmat \* A, dvector \* b, INT L, const REAL w, INT \* mark, const INT order )

SOR smoother with C/F ordering for Au=b.

### **Parameters**

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations
W	Over-relaxation weight
mark	C/F marker array
order	C/F ordering: -1: F-first; 1: C-first

### **Author**

Zhiyang Zhou

Date

2010/11/12

Modified by Chunsheng Feng, Zheng Li on 08/29/2012

Definition at line 873 of file smoother\_csr.c.

# 9.88 smoother\_csr\_cr.c File Reference

Smoothers for dCSRmat matrices using compatible relaxation.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

### **Functions**

void fasp\_smoother\_dcsr\_gscr (INT pt, INT n, REAL \*u, INT \*ia, INT \*ja, REAL \*a, REAL \*b, INT L, INT \*CF)
 Gauss Seidel method restriced to a block.

### 9.88.1 Detailed Description

Smoothers for dCSRmat matrices using compatible relaxation.

Note

Restricted-smoothers for compatible relaxation, C/F smoothing, etc.

Definition in file smoother\_csr\_cr.c.

### 9.88.2 Function Documentation

```
9.88.2.1 void fasp_smoother_dcsr_gscr ( INT pt, INT n, REAL * u, INT * ia, INT * ja, REAL * a, REAL * b, INT L, INT * CF )
```

Gauss Seidel method restriced to a block.

#### **Parameters**

pt	Relax type, e.g., cpt, fpt, etc
n	Number of variables
и	Iterated solution
ia	Row pointer
ja	Column index
а	Pointers to sparse matrix values in CSR format
b	Pointer to right hand side – remove later also as MG relaxation on error eqn
L	Number of iterations
CF	Marker for C, F points

#### Author

James Brannick

Date

09/07/2010

Note

Gauss Seidel CR smoother (Smoother\_Type = 99)

Definition at line 38 of file smoother\_csr\_cr.c.

# 9.89 smoother\_csr\_poly.c File Reference

Smoothers for dCSRmat matrices using poly. approx. to  $A^{-1}$ .

```
#include <math.h>
#include <time.h>
#include <float.h>
#include <limits.h>
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

- void fasp\_smoother\_dcsr\_poly (dCSRmat \*Amat, dvector \*brhs, dvector \*usol, INT n, INT ndeg, INT L)
   poly approx to A^{-1} as MG smoother
- void fasp\_smoother\_dcsr\_poly\_old (dCSRmat \*Amat, dvector \*brhs, dvector \*usol, INT n, INT ndeg, INT L)
   poly approx to A^{-1} as MG smoother: JK&LTZ2010

### 9.89.1 Detailed Description

Smoothers for dCSRmat matrices using poly. approx. to  $A^{\land}$ {-1}.

Definition in file smoother\_csr\_poly.c.

### 9.89.2 Function Documentation

9.89.2.1 void fasp\_smoother\_dcsr\_poly ( dCSRmat \* Amat, dvector \* brhs, dvector \* usol, INT n, INT ndeg, INT L)

poly approx to  $A^{-1}$  as MG smoother

#### **Parameters**

Amat	Pointer to stiffness matrix, consider square matrix.
brhs	Pointer to right hand side
usol	Pointer to solution
n	Problem size
ndeg	Degree of poly
L	Number of iterations

#### **Author**

Fei Cao, Xiaozhe Hu

Date

05/24/2012

Definition at line 46 of file smoother\_csr\_poly.c.

9.89.2.2 void fasp\_smoother\_dcsr\_poly\_old ( dCSRmat \* Amat, dvector \* brhs, dvector \* usol, INT n, INT ndeg, INT L )

poly approx to A^{-1} as MG smoother: JK&LTZ2010

Amat	Pointer to stiffness matrix
brhs	Pointer to right hand side
usol	Pointer to solution
n	Problem size
ndeg	Degree of poly
L	Number of iterations

#### **Author**

James Brannick and Ludmil T Zikatanov

#### Date

06/28/2010

Modified by Chunsheng Feng, Zheng Li on 10/18/2012

Definition at line 141 of file smoother\_csr\_poly.c.

# 9.90 smoother str.c File Reference

Smoothers for dSTRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

### **Functions**

• void fasp\_smoother\_dstr\_jacobi (dSTRmat \*A, dvector \*b, dvector \*u)

Jacobi method as the smoother.

Gauss-Seidel method as the smoother in the ascending manner.

- void fasp\_smoother\_dstr\_jacobi1 (dSTRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv)
   Jacobi method as the smoother with diag\_inv given.
- void fasp\_smoother\_dstr\_gs (dSTRmat \*A, dvector \*b, dvector \*u, INT order, INT \*mark)
   Gauss-Seidel method as the smoother.
- void fasp\_smoother\_dstr\_gs1 (dSTRmat \*A, dvector \*b, dvector \*u, INT order, INT \*mark, REAL \*diaginv)

  Gauss-Seidel method as the smoother with diag\_inv given.
- void fasp\_smoother\_dstr\_gs\_ascend (dSTRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv)
- void fasp\_smoother\_dstr\_gs\_descend (dSTRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv)
- Gauss-Seidel method as the smoother in the descending manner.

   void fasp\_smoother\_dstr\_gs\_order (dSTRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv, INT \*mark)
- Gauss method as the smoother in the user-defined order.
- void fasp\_smoother\_dstr\_gs\_cf (dSTRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv, INT \*mark, INT order)
   Gauss method as the smoother in the C-F manner.
- void fasp\_smoother\_dstr\_sor (dSTRmat \*A, dvector \*b, dvector \*u, INT order, INT \*mark, REAL weight) SOR method as the smoother.

void fasp\_smoother\_dstr\_sor1 (dSTRmat \*A, dvector \*b, dvector \*u, INT order, INT \*mark, REAL \*diaginv, REAL weight)

SOR method as the smoother.

• void fasp\_smoother\_dstr\_sor\_ascend (dSTRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv, REAL weight) SOR method as the smoother in the ascending manner.

void fasp\_smoother\_dstr\_sor\_descend (dSTRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv, REAL weight)
 SOR method as the smoother in the descending manner.

void fasp\_smoother\_dstr\_sor\_order (dSTRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv, INT \*mark, REAL weight)

SOR method as the smoother in the user-defined order.

Generate inverse of diagonal block for block smoothers.

 void fasp\_smoother\_dstr\_sor\_cf (dSTRmat \*A, dvector \*b, dvector \*u, REAL \*diaginv, INT \*mark, INT order, REAL weight)

SOR method as the smoother in the C-F manner.

 $\bullet \ \ void \ fasp\_generate\_diaginv\_block \ (dSTRmat \ *A, ivector \ *neigh, \ dvector \ *diaginv, ivector \ *pivot)\\$ 

void fasp\_smoother\_dstr\_schwarz (dSTRmat \*A, dvector \*b, dvector \*u, dvector \*diaginv, ivector \*pivot, ivector \*neigh, ivector \*order)

Schwarz method as the smoother.

### 9.90.1 Detailed Description

Smoothers for dSTRmat matrices.

Definition in file smoother\_str.c.

#### 9.90.2 Function Documentation

9.90.2.1 void fasp\_generate\_diaginv\_block ( dSTRmat \* A, ivector \* neigh, dvector \* diaginv, ivector \* pivot )

Generate inverse of diagonal block for block smoothers.

### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
neigh	Pointer to ivector: neighborhoods
diaginv	Pointer to dvector: the inverse of the diagonals
pivot	Pointer to ivector: the pivot of diagonal blocks

#### Author

Xiaozhe Hu

Date

10/01/2011

Definition at line 1517 of file smoother\_str.c.

9.90.2.2 void fasp\_smoother\_dstr\_gs ( dSTRmat \* A, dvector \* b, dvector \* u, INT order, INT \* mark )

Gauss-Seidel method as the smoother.

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending manner D-ESCEND 21: in descending manner If mark != NULL USERDEFINED 0: in the user-defined manner CPFIRST 1: C-points first and then F-points FPFIRST -1: F-points first and then C-points
mark	Pointer to the user-defined ordering(when order=0) or CF_marker array(when order!=0)

#### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 202 of file smoother\_str.c.

9.90.2.3 void fasp\_smoother\_dstr\_gs1 ( dSTRmat \* A, dvector \* b, dvector \* u, INT order, INT \* mark, REAL \* diaginv )

Gauss-Seidel method as the smoother with diag\_inv given.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending manner D-ESCEND 21: in descending manner If mark != NULL USERDEFINED 0: in the user-defined manner CPFIRST 1: C-points first and then F-points FPFIRST -1: F-points first and then C-points
mark	Pointer to the user-defined ordering(when order=0) or CF_marker array(when order!=0)
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1

### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 261 of file smoother\_str.c.

9.90.2.4 void fasp\_smoother\_dstr\_gs\_ascend ( dSTRmat\*A, dvector\*b, dvector\*u, REAL\*diaginv)

Gauss-Seidel method as the smoother in the ascending manner.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A->nc)=1

#### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 306 of file smoother\_str.c.

9.90.2.5 void fasp\_smoother\_dstr\_gs\_cf ( dSTRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv, INT \* mark, INT order )

Gauss method as the smoother in the C-F manner.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1
mark	Pointer to the user-defined order array
order	Flag to indicate the order for smoothing CPFIRST 1 : C-points first and then F-points FPFIRST
	-1 : F-points first and then C-points

#### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 660 of file smoother\_str.c.

9.90.2.6 void fasp\_smoother\_dstr\_gs\_descend ( dSTRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv )

Gauss-Seidel method as the smoother in the descending manner.

**Parameters** 

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1

#### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 421 of file smoother\_str.c.

9.90.2.7 void fasp\_smoother\_dstr\_gs\_order ( dSTRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv, INT \* mark )

Gauss method as the smoother in the user-defined order.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1
mark	Pointer to the user-defined order array

#### Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 538 of file smoother\_str.c.

9.90.2.8 void fasp\_smoother\_dstr\_jacobi ( dSTRmat \* A, dvector \* b, dvector \* u )

Jacobi method as the smoother.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
U	Pointer to dvector: the unknowns

### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 31 of file smoother\_str.c.

9.90.2.9 void fasp\_smoother\_dstr\_jacobi1 ( dSTRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv )

Jacobi method as the smoother with diag\_inv given.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1

#### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 79 of file smoother\_str.c.

9.90.2.10 void fasp\_smoother\_dstr\_schwarz ( dSTRmat \* A, dvector \* b, dvector \* u, dvector \* diaginv, ivector \* pivot, ivector \* neigh, ivector \* order)

Schwarz method as the smoother.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	Pointer to dvector: the inverse of the diagonals
pivot	Pointer to ivector: the pivot of diagonal blocks
neigh	Pointer to ivector: neighborhoods
order	Pointer to ivector: the smoothing order

**Author** 

Xiaozhe Hu

Date

10/01/2011

Definition at line 1639 of file smoother\_str.c.

9.90.2.11 void fasp\_smoother\_dstr\_sor ( dSTRmat \* A, dvector \* b, dvector \* u, INT order, INT \* mark, REAL weight )

SOR method as the smoother.

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending manner D-ESCEND 21: in descending manner If mark != NULL USERDEFINED 0: in the user-defined manner CPFIRST 1: C-points first and then F-points FPFIRST -1: F-points first and then C-points
mark	Pointer to the user-defined ordering(when order=0) or CF_marker array(when order!=0)
weight	Over-relaxation weight

#### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 851 of file smoother\_str.c.

9.90.2.12 void fasp\_smoother\_dstr\_sor1 ( dSTRmat \* A, dvector \* b, dvector \* u, INT order, INT \* mark, REAL \* diaginv, REAL weight )

SOR method as the smoother.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending manner D-ESCEND 21: in descending manner If mark != NULL USERDEFINED 0: in the user-defined manner CPFIRST 1: C-points first and then F-points FPFIRST -1: F-points first and then C-points
mark	Pointer to the user-defined ordering(when order=0) or CF_marker array(when order!=0)
diaginv	Inverse of the diagonal entries
weight	Over-relaxation weight

### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 912 of file smoother\_str.c.

9.90.2.13 void fasp\_smoother\_dstr\_sor\_ascend ( dSTRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv, REAL weight )

SOR method as the smoother in the ascending manner.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1
weight	Over-relaxation weight

#### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 958 of file smoother\_str.c.

9.90.2.14 void fasp\_smoother\_dstr\_sor\_cf ( dSTRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv, INT \* mark, INT order, REAL weight )

SOR method as the smoother in the C-F manner.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1
mark	Pointer to the user-defined order array
order	Flag to indicate the order for smoothing CPFIRST 1 : C-points first and then F-points FPFIRST
	-1: F-points first and then C-points
weight	Over-relaxation weight

#### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 1330 of file smoother\_str.c.

9.90.2.15 void fasp\_smoother\_dstr\_sor\_descend ( dSTRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv, REAL weight )

SOR method as the smoother in the descending manner.

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1
weight	Over-relaxation weight

### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 1078 of file smoother\_str.c.

9.90.2.16 void fasp\_smoother\_dstr\_sor\_order ( dSTRmat \* A, dvector \* b, dvector \* u, REAL \* diaginv, INT \* mark, REAL weight )

SOR method as the smoother in the user-defined order.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1
mark	Pointer to the user-defined order array
weight	Over-relaxation weight

### **Author**

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 1199 of file smoother\_str.c.

# 9.91 sparse\_block.c File Reference

Sparse matrix block operations.

```
#include <time.h>
#include "fasp.h"
#include "fasp_block.h"
#include "fasp_functs.h"
```

#### **Functions**

SHORT fasp\_dcsr\_getblk (dCSRmat \*A, INT \*Is, INT \*Js, INT m, INT n, dCSRmat \*B)
 Get a sub CSR matrix of A with specified rows and colums.

• SHORT fasp\_dbsr\_getblk (dBSRmat \*A, INT \*Is, INT \*Js, INT m, INT n, dBSRmat \*B)

Get a sub BSR matrix of A with specified rows and columns.

dCSRmat fasp\_dbsr\_getblk\_dcsr (dBSRmat \*A)

get dCSRmat block from a dBSRmat matrix

### 9.91.1 Detailed Description

Sparse matrix block operations.

Definition in file sparse block.c.

#### 9.91.2 Function Documentation

9.91.2.1 SHORT fasp\_dbsr\_getblk ( dBSRmat \* A, INT \* Is, INT \* Js, INT m, INT n, dBSRmat \* B )

Get a sub BSR matrix of A with specified rows and columns.

#### **Parameters**

Α	Pointer to dBSRmat BSR matrix
В	Pointer to dBSRmat BSR matrix
Is	Pointer to selected rows
Js	Pointer to selected colums
m	Number of selected rows
n	Number of selected colums

#### Returns

SUCCESS if successed, otherwise return error information.

#### **Author**

Shiquan Zhang, Xiaozhe Hu

Date

12/25/2010

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 132 of file sparse\_block.c.

9.91.2.2 dCSRmat fasp\_dbsr\_getblk\_dcsr ( dBSRmat \* A )

get dCSRmat block from a dBSRmat matrix

*A	Pointer to the BSR format matrix

#### Returns

dCSRmat matrix if succeed, NULL if fail

**Author** 

Xiaozhe Hu

Date

03/16/2012

Definition at line 226 of file sparse\_block.c.

```
9.91.2.3 SHORT fasp_dcsr_getblk ( dCSRmat * A, INT * Is, INT * Js, INT m, INT n, dCSRmat * B )
```

Get a sub CSR matrix of A with specified rows and colums.

#### **Parameters**

Α	Pointer to dCSRmat matrix
В	Pointer to dCSRmat matrix
Is	Pointer to selected rows
Js	Pointer to selected colums
m	Number of selected rows
n	Number of selected colums

#### Returns

SUCCESS if successed, otherwise return error information.

**Author** 

Shiquan Zhang, Xiaozhe Hu

Date

12/25/2010

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 39 of file sparse\_block.c.

# 9.92 sparse\_bsr.c File Reference

Sparse matrix operations for dBSRmat matrices.

```
#include "fasp.h"
#include "fasp_functs.h"
```

#### **Functions**

dBSRmat fasp dbsr create (INT ROW, INT COL, INT NNZ, INT nb, INT storage manner)

Create BSR sparse matrix data memory space.

void fasp dbsr alloc (INT ROW, INT COL, INT NNZ, INT nb, INT storage manner, dBSRmat \*A)

Allocate memory space for BSR format sparse matrix.

void fasp\_dbsr\_free (dBSRmat \*A)

Free memeory space for BSR format sparse matrix.

void fasp dbsr null (dBSRmat \*A)

Initialize sparse matrix on structured grid.

void fasp\_dbsr\_cp (dBSRmat \*A, dBSRmat \*B)

copy a dCSRmat to a new one B=A

INT fasp dbsr trans (dBSRmat \*A, dBSRmat \*AT)

Find  $A^{\wedge}T$  from given dBSRmat matrix A.

SHORT fasp\_dbsr\_diagpref (dBSRmat \*A)

Reorder the column and data arrays of a square BSR matrix, so that the first entry in each row is the diagonal one.

dvector fasp\_dbsr\_getdiaginv (dBSRmat \*A)

Get  $D^{\wedge}$ {-1} of matrix A.

dBSRmat fasp\_dbsr\_diaginv (dBSRmat \*A)

Compute  $B := D^{\setminus} \{-1\} * A$ , where 'D' is the block diagonal part of A.

dBSRmat fasp\_dbsr\_diaginv2 (dBSRmat \*A, REAL \*diaginv)

Compute  $B := D^{\setminus} \{-1\} * A$ , where 'D' is the block diagonal part of A.

dBSRmat fasp\_dbsr\_diaginv3 (dBSRmat \*A, REAL \*diaginv)

Compute  $B := D^{\setminus} \{-1\} * A$ , where 'D' is the block diagonal part of A.

dBSRmat fasp\_dbsr\_diaginv4 (dBSRmat \*A, REAL \*diaginv)
 Compute B := D^{-1}\*A, where 'D' is the block diagonal part of A.

void fasp dbsr getdiag (INT n, dBSRmat \*A, REAL \*diag)

Abstract the diagonal blocks of a BSR matrix.

### 9.92.1 Detailed Description

Sparse matrix operations for dBSRmat matrices.

Definition in file sparse\_bsr.c.

### 9.92.2 Function Documentation

9.92.2.1 void fasp\_dbsr\_alloc ( INT ROW, INT COL, INT NNZ, INT nb, INT storage\_manner, dBSRmat \* A )

Allocate memory space for BSR format sparse matrix.

#### **Parameters**

ROW	Number of rows of block
COL	Number of columns of block

NNZ	Number of nonzero blocks
nb	Dimension of exch block
storage_manner	Storage manner for each sub-block
Α	Pointer to new dBSRmat matrix

**Author** 

Xiaozhe Hu

Date

10/26/2010

Definition at line 84 of file sparse\_bsr.c.

9.92.2.2 void fasp\_dbsr\_cp ( dBSRmat \* A, dBSRmat \* B )

copy a dCSRmat to a new one B=A

#### **Parameters**

Α	Pointer to the dBSRmat matrix
В	Pointer to the dBSRmat matrix

**Author** 

Xiaozhe Hu

Date

08/07/2011

Definition at line 177 of file sparse\_bsr.c.

9.92.2.3 dBSRmat fasp\_dbsr\_create ( INT ROW, INT COL, INT NNZ, INT nb, INT storage\_manner )

Create BSR sparse matrix data memory space.

### **Parameters**

ROW	Number of rows of block
COL	Number of columns of block
NNZ	Number of nonzero blocks
nb	Dimension of exch block
storage_manner	Storage manner for each sub-block

#### Returns

A The new dBSRmat matrix

**Author** 

Xiaozhe Hu

Date

10/26/2010

Definition at line 33 of file sparse\_bsr.c.

9.92.2.4 dBSRmat fasp\_dbsr\_diaginv ( dBSRmat \* A )

Compute B :=  $D^{-1}*A$ , where 'D' is the block diagonal part of A.

**Parameters** 

A Pointer to the dBSRmat matrix

**Author** 

Zhiyang Zhou

Date

2010/10/26

Note

Works for general nb (Xiaozhe)

Modified by Chunsheng Feng, Zheng Li on 08/25/2012

Definition at line 501 of file sparse\_bsr.c.

9.92.2.5 dBSRmat fasp\_dbsr\_diaginv2 ( dBSRmat \* A, REAL \* diaginv )

Compute B :=  $D^{\{-1\}}*A$ , where 'D' is the block diagonal part of A.

**Parameters** 

Α	Pointer to the dBSRmat matrix
diaginv	Pointer to the inverses of all the diagonal blocks

**Author** 

Zhiyang Zhou

Date

2010/11/07

Note

Works for general nb (Xiaozhe)

Modified by Chunsheng Feng, Zheng Li on 08/25/2012

Definition at line 663 of file sparse\_bsr.c.

9.92.2.6 dBSRmat fasp\_dbsr\_diaginv3 ( dBSRmat \* A, REAL \* diaginv )

Compute B :=  $D^{-1}*A$ , where 'D' is the block diagonal part of A.

## **Parameters**

A	Pointer to the dBSRmat matrix
diaginv	Pointer to the inverses of all the diagonal blocks

#### Returns

BSR matrix after diagonal scaling

**Author** 

Xiaozhe Hu

Date

12/25/2010

Note

Works for general nb (Xiaozhe)

Modified by Xiaozhe Hu on 05/26/2012

Definition at line 765 of file sparse\_bsr.c.

9.92.2.7 dBSRmat fasp\_dbsr\_diaginv4 ( dBSRmat \* A, REAL \* diaginv )

Compute B :=  $D^{-1}*A$ , where 'D' is the block diagonal part of A.

### **Parameters**

Α	Pointer to the dBSRmat matrix
diaginv	Pointer to the inverses of all the diagonal blocks

## Returns

BSR matrix after diagonal scaling

Note

Works for general nb (Xiaozhe)

A is preordered that the first block of each row is the diagonal block!

**Author** 

Xiaozhe Hu

Date

03/12/2011

Modified by Chunsheng Feng, Zheng Li on 08/26/2012

Definition at line 1123 of file sparse\_bsr.c.

9.92.2.8 SHORT fasp\_dbsr\_diagpref ( dBSRmat \* A )

Reorder the column and data arrays of a square BSR matrix, so that the first entry in each row is the diagonal one.

**Parameters** 

A Pointer to the BSR matrix

**Author** 

Xiaozhe Hu

Date

03/10/2011

Author

Chunsheng Feng, Zheng Li

Date

09/02/2012

Note

Reordering is done in place.

Definition at line 288 of file sparse\_bsr.c.

9.92.2.9 void fasp\_dbsr\_free ( dBSRmat \* A )

Free memeory space for BSR format sparse matrix.

**Parameters** 

A Pointer to the dBSRmat matrix

**Author** 

Xiaozhe Hu

Date

10/26/2010

Definition at line 129 of file sparse\_bsr.c.

9.92.2.10 fasp\_dbsr\_getdiag ( INT n, dBSRmat \* A, REAL \* diag )

Abstract the diagonal blocks of a BSR matrix.

## **Parameters**

n	Number of blocks to get
Α	Pointer to the 'dBSRmat' type matrix
diag	Pointer to array which stores the diagonal blocks in row by row manner

**Author** 

Zhiyang Zhou

Date

2010/10/26

Note

Works for general nb (Xiaozhe)

Modified by Chunsheng Feng, Zheng Li on 08/25/2012

Definition at line 1416 of file sparse\_bsr.c.

9.92.2.11 dvector fasp\_dbsr\_getdiaginv ( dBSRmat \* A )

Get  $D^{\setminus}\{-1\}$  of matrix A.

**Parameters** 

|--|

**Author** 

Xiaozhe Hu

Date

02/19/2013

Note

Works for general nb (Xiaozhe)

Definition at line 397 of file sparse\_bsr.c.

9.92.2.12 void fasp\_dbsr\_null ( dBSRmat \* A )

Initialize sparse matrix on structured grid.

**Parameters** 

A Pointer to the dBSRmat matrix

**Author** 

Xiaozhe Hu

Date

10/26/2010

Definition at line 154 of file sparse\_bsr.c.

```
9.92.2.13 INT fasp_dbsr_trans ( dBSRmat * A, dBSRmat * AT )
```

Find A<sup>\(\Delta\)</sup>T from given dBSRmat matrix A.

#### **Parameters**

Α	Pointer to the dBSRmat matrix
AT	Pointer to the transpose of dBSRmat matrix A

#### **Author**

Chunsheng FENG

Date

2011/06/08

Modified by Xiaozhe Hu (08/06/2011)

Definition at line 204 of file sparse\_bsr.c.

# 9.93 sparse\_coo.c File Reference

Sparse matrix operations for dCOOmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

dCOOmat fasp\_dcoo\_create (INT m, INT n, INT nnz)

Create IJ sparse matrix data memory space.

void fasp\_dcoo\_alloc (const INT m, const INT n, const INT nnz, dCOOmat \*A)

Allocate COO sparse matrix memory space.

void fasp\_dcoo\_free (dCOOmat \*A)

Free IJ sparse matrix data memeory space.

void fasp\_dcoo\_shift (dCOOmat \*A, INT offset)

Reindex a REAL matrix in IJ format to make the index starting from 0 or 1.

## 9.93.1 Detailed Description

Sparse matrix operations for dCOOmat matrices.

Definition in file sparse\_coo.c.

## 9.93.2 Function Documentation

9.93.2.1 void fasp\_dcoo\_alloc ( const INT m, const INT n, const INT nnz, dCOOmat \* A )

Allocate COO sparse matrix memory space.

## **Parameters**

m	Number of rows
n	Number of columns
nnz	Number of nonzeros
Α	Pointer to the dCSRmat matrix

## **Author**

Xiaozhe Hu

Date

03/25/2013

Definition at line 62 of file sparse\_coo.c.

9.93.2.2 dCOOmat fasp\_dcoo\_create ( INT m, INT n, INT nnz )

Create IJ sparse matrix data memory space.

## **Parameters**

т	Number of rows
n	Number of columns
nnz	Number of nonzeros

## Returns

A The new dCOOmat matrix

**Author** 

Chensong Zhang

Date

2010/04/06

Definition at line 34 of file sparse\_coo.c.

9.93.2.3 void fasp\_dcoo\_free ( dCOOmat \* A )

Free IJ sparse matrix data memeory space.

## **Parameters**

Α	Pointer to the dCOOmat matrix

**Author** 

Chensong Zhang

Date

2010/04/03

Definition at line 95 of file sparse\_coo.c.

```
9.93.2.4 void fasp_dcoo_shift ( dCOOmat * A, INT offset )
```

Reindex a REAL matrix in IJ format to make the index starting from 0 or 1.

#### **Parameters**

Α	Pointer to IJ matrix
offset	Size of offset (1 or -1)

## **Author**

Chensong Zhang

Date

2010/04/06

Modified by Chunsheng Feng, Zheng Li on 08/25/2012

Definition at line 117 of file sparse\_coo.c.

## 9.94 sparse\_csr.c File Reference

Sparse matrix operations for dCSRmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

dCSRmat fasp\_dcsr\_create (const INT m, const INT n, const INT nnz)

Create CSR sparse matrix data memory space.

iCSRmat fasp\_icsr\_create (const INT m, const INT n, const INT nnz)

Create CSR sparse matrix data memory space.

void fasp dcsr alloc (const INT m, const INT n, const INT nnz, dCSRmat \*A)

Allocate CSR sparse matrix memory space.

void fasp\_dcsr\_free (dCSRmat \*A)

Free CSR sparse matrix data memeory space.

void fasp icsr free (iCSRmat \*A)

Free CSR sparse matrix data memeory space.

void fasp\_dcsr\_null (dCSRmat \*A)

Initialize CSR sparse matrix.

void fasp\_icsr\_null (iCSRmat \*A)

Initialize CSR sparse matrix.

dCSRmat fasp dcsr perm (dCSRmat \*A, INT \*P)

Apply permutation of A, i.e. Aperm=PAP' by the orders given in P.

void fasp\_dcsr\_sort (dCSRmat \*A)

Sort each row of A in ascending order w.r.t. column indices.

void fasp\_dcsr\_getdiag (INT n, dCSRmat \*A, dvector \*diag)

Get first n diagonal entries of a CSR matrix A.

void fasp dcsr getcol (const INT n, dCSRmat \*A, REAL \*col)

Get the n-th column of a CSR matrix A.

void fasp dcsr diagpref (dCSRmat \*A)

Re-order the column and data arrays of a CSR matrix, so that the first entry in each row is the diagonal.

SHORT fasp\_dcsr\_regdiag (dCSRmat \*A, REAL value)

Regularize diagonal entries of a CSR sparse matrix.

void fasp\_icsr\_cp (iCSRmat \*A, iCSRmat \*B)

Copy a iCSRmat to a new one B=A.

void fasp\_dcsr\_cp (dCSRmat \*A, dCSRmat \*B)

copy a dCSRmat to a new one B=A

void fasp icsr trans (iCSRmat \*A, iCSRmat \*AT)

Find transpose of iCSRmat matrix A.

INT fasp dcsr trans (dCSRmat \*A, dCSRmat \*AT)

Find tranpose of dCSRmat matrix A.

- void fasp\_dcsr\_transpose (INT \*row[2], INT \*col[2], REAL \*val[2], INT \*nn, INT \*tniz)
- void fasp\_dcsr\_compress (dCSRmat \*A, dCSRmat \*B, REAL dtol)

Compress a CSR matrix A and store in CSR matrix B by dropping small entries abs(aij)<=dtol.

SHORT fasp\_dcsr\_compress\_inplace (dCSRmat \*A, REAL dtol)

Compress a CSR matrix A IN PLACE by dropping small entries abs(aij)<=dtol.

void fasp\_dcsr\_shift (dCSRmat \*A, INT offset)

Reindex a REAL matrix in CSR format to make the index starting from 0 or 1.

void fasp\_dcsr\_symdiagscale (dCSRmat \*A, dvector \*diag)

Symmetric diagonal scaling  $D^{\wedge}$  {-1/2} $AD^{\wedge}$  {-1/2}.

dCSRmat fasp\_dcsr\_sympat (dCSRmat \*A)

Symmetrize the parttarn of a dCSRmat matrix.

void fasp\_dcsr\_multicoloring (dCSRmat \*A, INT \*flags, INT \*groups)

Use the greedy multicoloring to get color groups of the adjacency graph of A.

## 9.94.1 Detailed Description

Sparse matrix operations for dCSRmat matrices.

Definition in file sparse csr.c.

## 9.94.2 Function Documentation

9.94.2.1 void fasp\_dcsr\_alloc ( const INT m, const INT n, const INT nnz, dCSRmat \* A )

Allocate CSR sparse matrix memory space.

## **Parameters**

m	Number of rows
n	Number of columns
nnz	Number of nonzeros
Α	Pointer to the dCSRmat matrix

## **Author**

Chensong Zhang

Date

2010/04/06

Definition at line 125 of file sparse\_csr.c.

9.94.2.2 void fasp\_dcsr\_compress ( dCSRmat \* A, dCSRmat \* B, REAL dtol )

Compress a CSR matrix A and store in CSR matrix B by dropping small entries abs(aij)<=dtol.

## **Parameters**

Α	Pointer to dCSRmat CSR matrix
В	Pointer to dCSRmat CSR matrix
dtol	Drop tolerance

## **Author**

Shiquan Zhang

Date

03/10/2010

Modified by Chunsheng Feng, Zheng Li on 08/25/2012

Definition at line 960 of file sparse\_csr.c.

9.94.2.3 SHORT fasp\_dcsr\_compress\_inplace ( dCSRmat \* A, REAL dtol )

Compress a CSR matrix A IN PLACE by dropping small entries abs(aij)<=dtol.

## **Parameters**

Α	Pointer to dCSRmat CSR matrix
dtol	Drop tolerance

**Author** 

Xiaozhe Hu

Date

12/25/2010

Modified by Chensong on 02/21/2013

Note

This routine can be modified for filtering.

Definition at line 1040 of file sparse\_csr.c.

9.94.2.4 void fasp\_dcsr\_cp ( dCSRmat \* A, dCSRmat \* B )

copy a dCSRmat to a new one B=A

## **Parameters**

ſ	Α	Pointer to the dCSRmat matrix
ſ	В	Pointer to the dCSRmat matrix

**Author** 

Chensong Zhang

Date

04/06/2010

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 722 of file sparse\_csr.c.

9.94.2.5 dCSRmat fasp\_dcsr\_create ( const INT m, const INT n, const INT nnz )

Create CSR sparse matrix data memory space.

## **Parameters**

т	Number of rows
n	Number of columns

nnz Number of nonzeros Returns A the new dCSRmat matrix **Author** Chensong Zhang Date 2010/04/06 Definition at line 34 of file sparse\_csr.c. 9.94.2.6 void fasp\_dcsr\_diagpref ( dCSRmat \* A ) Re-order the column and data arrays of a CSR matrix, so that the first entry in each row is the diagonal. **Parameters** Pointer to the matrix to be re-ordered Author Zhiyang Zhou Date 09/09/2010 Author Chunsheng Feng, Zheng Li Date 09/02/2012 Note Reordering is done in place. Modified by Chensong Zhang on Dec/21/2012 Definition at line 551 of file sparse\_csr.c. 9.94.2.7 void fasp\_dcsr\_free ( dCSRmat \* A ) Free CSR sparse matrix data memeory space.

## **Parameters**

Α	Pointer to the dCSRmat matrix

**Author** 

Chensong Zhang

Date

2010/04/06

Definition at line 166 of file sparse\_csr.c.

9.94.2.8 void fasp\_dcsr\_getcol ( const INT n, dCSRmat \* A, REAL \* col )

Get the n-th column of a CSR matrix A.

## **Parameters**

n	Index of a column of A (0 $\leq$ n $\leq$ A.col-1)
Α	Pointer to dCSRmat CSR matrix
col	Pointer to the column

## Author

Xiaozhe Hu

Date

11/07/2009

Modified by Chunsheng Feng, Zheng Li on 07/08/2012

Definition at line 472 of file sparse\_csr.c.

9.94.2.9 void fasp\_dcsr\_getdiag ( INT n, dCSRmat \* A, dvector \* diag )

Get first n diagonal entries of a CSR matrix A.

## **Parameters**

n	Number of diag entries to get (if n=0, then get all diagonal entries)
Α	Pointer to dCSRmat CSR matrix
diag	Pointer to the diagonal as a dvector

## **Author**

Chensong Zhang

Date

05/20/2009

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 408 of file sparse\_csr.c.

9.94.2.10 void fasp\_dcsr\_multicoloring ( dCSRmat \* A, INT \* flags, INT \* groups )

Use the greedy multicoloring to get color groups of the adjacency graph of A.

## **Parameters**

Α	Input dCSRmat
flags	flags for the independent group
groups	Return group numbers

**Author** 

Chunsheng Feng

Date

09/15/2012

Definition at line 1272 of file sparse\_csr.c.

9.94.2.11 void fasp\_dcsr\_null ( dCSRmat \* A )

Initialize CSR sparse matrix.

## **Parameters**

Α	Pointer to the dCSRmat matrix

**Author** 

Chensong Zhang

Date

2010/04/03

Definition at line 204 of file sparse\_csr.c.

9.94.2.12 dCSRmat fasp\_dcsr\_perm ( dCSRmat \* A, INT \* P )

Apply permutation of A, i.e. Aperm=PAP' by the orders given in P.

## **Parameters**

Α	Pointer to the oringinal dCSRmat matrix
Р	Pointer to orders

### Returns

The new ordered dCSRmat matrix if succeed, NULL if fail

**Author** 

Shiquan Zhang

Date

03/10/2010

Note

P[i] = k means k-th row and column become i-th row and column!

Modified by Chunsheng Feng, Zheng Li on 07/12/2012

Definition at line 245 of file sparse\_csr.c.

9.94.2.13 SHORT fasp\_dcsr\_regdiag ( dCSRmat \* A, REAL value )

Regularize diagonal entries of a CSR sparse matrix.

## **Parameters**

ſ	Α	Pointer to the dCSRmat matrix
	value	Set a value on diag(A) which is too close to zero to "value"

#### Returns

SUCCESS if no diagonal entry is close to zero, else ERROR

**Author** 

Shiquan Zhang

Date

11/07/2009

Definition at line 658 of file sparse\_csr.c.

9.94.2.14 void fasp\_dcsr\_shift ( dCSRmat \* A, INT offset )

Reindex a REAL matrix in CSR format to make the index starting from 0 or 1.

### **Parameters**

Α	Pointer to CSR matrix
offset	Size of offset (1 or -1)

**Author** 

Chensong Zhang

Date

04/06/2010

Modified by chunsheng Feng, Zheng Li on 07/11/2012

Definition at line 1088 of file sparse\_csr.c.

9.94.2.15 void fasp\_dcsr\_sort ( dCSRmat \* A )

Sort each row of A in ascending order w.r.t. column indices.

## **Parameters**

A Pointer to the dCSRmat matrix

**Author** 

Shiquan Zhang

Date

06/10/2010

Definition at line 356 of file sparse\_csr.c.

9.94.2.16 void fasp\_dcsr\_symdiagscale ( dCSRmat \* A, dvector \* diag )

Symmetric diagonal scaling  $D^{-1/2}AD^{-1/2}$ .

#### **Parameters**

Α	Pointer to the dCSRmat matrix
diag	Pointer to the diagonal entries

#### **Author**

Xiaozhe Hu

Date

01/31/2011

Modified by Chunsheng Feng, Zheng Li on 07/11/2012

Definition at line 1151 of file sparse\_csr.c.

9.94.2.17 dCSRmat fasp\_dcsr\_sympat ( dCSRmat \* A )

Symmetrize the parttarn of a dCSRmat matrix.

## **Parameters**

*A   pointer to the dCSRmat matrix
------------------------------------

## Returns

symmetrized the dCSRmat matrix

**Author** 

Xiaozhe Hu

Date

03/21/2011

Definition at line 1238 of file sparse\_csr.c.

9.94.2.18 void fasp\_dcsr\_trans ( dCSRmat \* A, dCSRmat \* AT)

Find tranpose of dCSRmat matrix A.

## **Parameters**

Α	Pointer to the dCSRmat matrix
AT	Pointer to the transpose of dCSRmat matrix A (output)

## Author

Chensong Zhang

Date

04/06/2010

Modified by Chunsheng Feng, Zheng Li on 06/20/2012

Definition at line 828 of file sparse\_csr.c.

9.94.2.19 void fasp\_icsr\_cp ( iCSRmat \* A, iCSRmat \* B )

Copy a iCSRmat to a new one B=A.

#### **Parameters**

Α	Pointer to the iCSRmat matrix
В	Pointer to the iCSRmat matrix

## **Author**

Chensong Zhang

Date

05/16/2013

Definition at line 697 of file sparse\_csr.c.

9.94.2.20 iCSRmat fasp\_icsr\_create ( const INT m, const INT n, const INT nnz )

Create CSR sparse matrix data memory space.

## **Parameters**

т	Number of rows
n	Number of columns
nnz	Number of nonzeros

## Returns

A the new iCSRmat matrix

## **Author**

Chensong Zhang

Date

2010/04/06

Definition at line 80 of file sparse\_csr.c.

9.94.2.21 void fasp\_icsr\_free ( iCSRmat \* A )

Free CSR sparse matrix data memeory space.

**Parameters** 

A Pointer to the iCSRmat matrix

**Author** 

Chensong Zhang

Date

2010/04/06

Definition at line 185 of file sparse\_csr.c.

9.94.2.22 void fasp\_icsr\_null ( iCSRmat \* A )

Initialize CSR sparse matrix.

**Parameters** 

A Pointer to the iCSRmat matrix

**Author** 

Chensong Zhang

Date

2010/04/03

Definition at line 221 of file sparse\_csr.c.

9.94.2.23 void fasp\_icsr\_trans ( iCSRmat \* A, iCSRmat \* AT )

Find transpose of iCSRmat matrix A.

**Parameters** 

A Pointer to the iCSRmat matrix A

## AT Pointer to the iCSRmat matrix A'

Returns

The transpose of iCSRmat matrix A

**Author** 

Chensong Zhang

Date

04/06/2010

Modified by Chunsheng Feng, Zheng Li on 06/20/2012

Definition at line 749 of file sparse\_csr.c.

# 9.95 sparse\_csrl.c File Reference

Sparse matrix operations for dCSRLmat matrices.

```
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

dCSRLmat \* fasp\_dcsrl\_create (INT num\_rows, INT num\_cols, INT num\_nonzeros)

Create a dCSRLmat object.

void fasp\_dcsrl\_free (dCSRLmat \*A)

Destroy a dCSRLmat object.

## 9.95.1 Detailed Description

Sparse matrix operations for dCSRLmat matrices.

Note

For details of CSRL format, refer to Optimizing sparse matrix vector product computations using unroll and jam by John Mellor-Crummey and John Garvin, Tech Report Rice Univ, Aug 2002.

Definition in file sparse\_csrl.c.

## 9.95.2 Function Documentation

9.95.2.1 dCSRLmat \* fasp\_dcsrl\_create ( INT num\_rows, INT num\_cols, INT num\_nonzeros )

Create a dCSRLmat object.

## **Parameters**

num_rows	Number of rows
num_cols	Number of cols
num_nonzeros	Number of nonzero entries

#### **Author**

Zhiyang Zhou

Date

01/07/2001

Definition at line 30 of file sparse\_csrl.c.

```
9.95.2.2 void fasp_dcsrl_free ( dCSRLmat * A )
```

Destroy a dCSRLmat object.

#### **Parameters**

Α	Pointer to the dCSRLmat type matrix
---	-------------------------------------

#### **Author**

Zhiyang Zhou

Date

01/07/2011

Definition at line 58 of file sparse\_csrl.c.

# 9.96 sparse\_str.c File Reference

Sparse matrix operations for dSTRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

void fasp\_dstr\_null (dSTRmat \*A)

Initialize sparse matrix on structured grid.

dSTRmat fasp\_dstr\_create (INT nx, INT ny, INT nz, INT nc, INT nband, INT \*offsets)

Create STR sparse matrix data memory space.

• void fasp\_dstr\_alloc (INT nx, INT ny, INT nz, INT nxy, INT ngrid, INT nband, INT nc, INT \*offsets, dSTRmat \*A)

Allocate STR sparse matrix memory space.

void fasp\_dstr\_free (dSTRmat \*A)

Free STR sparse matrix data memeory space.

void fasp\_dstr\_cp (dSTRmat \*A, dSTRmat \*A1)

Copy a dSTRmat to a new one A1=A.

## 9.96.1 Detailed Description

Sparse matrix operations for dSTRmat matrices.

Definition in file sparse\_str.c.

## 9.96.2 Function Documentation

9.96.2.1 void fasp\_dstr\_alloc (INT nx, INT ny, INT nz, INT nxy, INT ngrid, INT nband, INT nc, INT \* offsets, dSTRmat \* A )

Allocate STR sparse matrix memory space.

#### **Parameters**

nx	Number of grids in x direction
ny	Number of grids in y direction
nz	Number of grids in z direction
nxy	Number of grids in x-y plane
ngrid	Number of grids
nband	Number of off-diagonal bands
nc	Number of components
offsets	Shift from diagonal
Α	Pointer to the dSTRmat matrix

#### **Author**

Shiquan Zhang, Xiaozhe Hu

Date

05/17/2010

Definition at line 107 of file sparse\_str.c.

9.96.2.2 void fasp\_dstr\_cp ( dSTRmat \* A, dSTRmat \* A1 )

Copy a dSTRmat to a new one A1=A.

## **Parameters**

Α	Pointer to the dSTRmat matrix
A1	Pointer to the dSTRmat matrix

## Author

Zhiyang Zhou

Date

04/21/2010

Definition at line 179 of file sparse\_str.c.

9.96.2.3 dSTRmat fasp\_dstr\_create ( INT nx, INT ny, INT nz, INT nc, INT nband, INT \* offsets )

Create STR sparse matrix data memory space.

#### **Parameters**

nx	Number of grids in x direction
ny	Number of grids in y direction
nz	Number of grids in z direction
nc	Number of components
nband	Number of off-diagonal bands
offsets	Shift from diagonal

## Returns

The dSTRmat matrix

## **Author**

Shiquan Zhang, Xiaozhe Hu

Date

05/17/2010

Definition at line 56 of file sparse\_str.c.

9.96.2.4 void fasp\_dstr\_free ( dSTRmat \* A )

Free STR sparse matrix data memeory space.

## **Parameters**

Α	Pointer to the dSTRmat matrix
---	-------------------------------

**Author** 

Shiquan Zhang, Xiaozhe Hu

Date

05/17/2010

Definition at line 150 of file sparse\_str.c.

9.96.2.5 void fasp\_dstr\_null ( dSTRmat \* A )

Initialize sparse matrix on structured grid.

#### **Parameters**

Α	Pointer to the dSTRmat matrix	7
---	-------------------------------	---

Author

Shiquan Zhang, Xiaozhe Hu

Date

05/17/2010

Definition at line 25 of file sparse str.c.

# 9.97 sparse\_util.c File Reference

Routines for sparse matrix operations.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

- void fasp\_sparse\_abybms\_ (INT \*ia, INT \*ja, INT \*ib, INT \*jb, INT \*nap, INT \*map, INT \*mbp, INT \*ic, INT \*jc)
   Multiplication of two sparse matrices: calculating the nonzero structure of the result if jc is not null. If jc is null only finds num of nonzeroes.
- void fasp\_sparse\_abyb\_ (INT \*ia, INT \*ja, REAL \*a, INT \*ib, INT \*jb, REAL \*b, INT \*nap, INT \*map, INT \*mbp, INT \*ic, INT \*jc, REAL \*c)

Multiplication of two sparse matrices: calculating the numerical values in the result.

- void fasp\_sparse\_iit\_ (INT \*ia, INT \*ja, INT \*na, INT \*ma, INT \*iat, INT \*jat)
   Transpose a boolean matrix (only given by ia, ja)
- void fasp\_sparse\_aat\_ (INT \*ia, INT \*ja, REAL \*a, INT \*na, INT \*ma, INT \*iat, INT \*jat, REAL \*at)
- transpose a boolean matrix (only given by ia, ja)
   void fasp\_sparse\_aplbms\_ (INT \*ia, INT \*ja, INT \*ib, INT \*jb, INT \*nab, INT \*mab, INT \*ic, INT \*jc)
  - Addition of two sparse matrices: calculating the nonzero structure of the result if jc is not null. if jc is null only finds num of nonzeroes.
- void fasp\_sparse\_aplusb\_ (INT \*ia, INT \*ja, REAL \*a, INT \*ib, INT \*jb, REAL \*b, INT \*nab, INT \*mab, INT \*ic, INT \*jc, REAL \*c)

Addition of two sparse matrices: calculating the numerical values in the result.

- void fasp\_sparse\_rapms\_ (INT \*ir, INT \*jr, INT \*ia, INT \*ja, INT \*jp, INT \*jp, INT \*nin, INT \*ncin, INT \*iac, INT \*jac, INT \*maxrout)
  - Calculates the nonzero structure of R\*A\*P, if jac is not null. If jac is null only finds num of nonzeroes.
- void fasp\_sparse\_wtams\_ (INT \*jw, INT \*ia, INT \*ja, INT \*nwp, INT \*map, INT \*jv, INT \*nvp, INT \*icp)
  - Finds the nonzeroes in the result of  $v^t = w^t A$ , where w is a sparse vector and A is sparse matrix. jv is an integer array containing the indices of the nonzero elements in the result.
- void fasp\_sparse\_wta\_ (INT \*jw, REAL \*w, INT \*ia, INT \*ja, REAL \*a, INT \*nwp, INT \*map, INT \*jv, REAL \*v, INT \*nvp)

Calculate  $v^{\wedge}t = w^{\wedge}t$  A, where w is a sparse vector and A is sparse matrix. v is an array of dimension = number of columns in A.

void fasp\_sparse\_ytxbig\_ (INT \*jy, REAL \*y, INT \*nyp, REAL \*x, REAL \*s)

Calculates  $s = y^{\wedge} t x$ . y-sparse, x - no.

- void fasp\_sparse\_ytx\_ (INT \*jy, REAL \*y, INT \*jx, REAL \*x, INT \*nyp, INT \*nxp, INT \*icp, REAL \*s) Calculates  $s = y^{h}t$  x. y is sparse, x is sparse.
- void fasp\_sparse\_rapcmp\_ (INT \*ir, INT \*jr, REAL \*r, INT \*ia, INT \*ja, REAL \*a, INT \*ipt, INT \*jpt, REAL \*pt, INT \*nin, INT \*ncin, INT \*iac, INT \*jac, REAL \*ac, INT \*idummy)

Calculates R\*A\*P after the nonzero structure of the result is known. iac,jac,ac have to be allocated before call to this function.

ivector fasp\_sparse\_MIS (dCSRmat \*A)

get the maximal independet set of a CSR matrix

## 9.97.1 Detailed Description

Routines for sparse matrix operations.

Note

Most algorithms work as follows: (a) Boolean operations (to determine the nonzero structure); (b) Numerical part, where the result is calculated.

: Parameter notation :1: is input; :0: is output; :10: is both

C-version: by Ludmil Zikatanov 2010-04-08 tested 2010-04-08

: Modifed Xiaozhe Hu 2010-10-18

Definition in file sparse\_util.c.

## 9.97.2 Function Documentation

```
9.97.2.1 void fasp_sparse_aat_ ( INT * ia, INT * ja, REAL * a, INT * na, INT * ma, INT * iat, INT * jat, REAL * at )
```

transpose a boolean matrix (only given by ia, ja)

#### **Parameters**

ia	array of row pointers (as usual in CSR)
ja	array of column indices
а	array of entries of teh input
na	number of rows of A
ma	number of cols of A
iat	array of row pointers in the result
jat	array of column indices
at	array of entries of the result

Definition at line 272 of file sparse\_util.c.

Multiplication of two sparse matrices: calculating the numerical values in the result.

## **Parameters**

ia	array of row pointers 1st multiplicand
ja	array of column indices 1st multiplicand
а	entries of the 1st multiplicand
ib	array of row pointers 2nd multiplicand
jb	array of column indices 2nd multiplicand
b	entries of the 2nd multiplicand
ic	array of row pointers in c=a*b
jc	array of column indices in c=a*b
С	entries of the result: c= a*b
nap	number of rows in the 1st multiplicand
тар	number of columns in the 1st multiplicand
mbp	number of columns in the 2nd multiplicand

Modified by Chensong Zhang on 09/11/2012

Definition at line 124 of file sparse\_util.c.

9.97.2.3 void fasp\_sparse\_abybms\_ ( INT \* ia, INT \* ja, INT \* ib, INT \* jb, INT \* nap, INT \* map, INT \* map

Multiplication of two sparse matrices: calculating the nonzero structure of the result if jc is not null. If jc is null only finds num of nonzeroes.

#### **Parameters**

ia	array of row pointers 1st multiplicand
ia	array of row pointers 1st multiplicand
ja	array of column indices 1st multiplicand
ib	array of row pointers 2nd multiplicand
jb	array of column indices 2nd multiplicand
nap	number of rows of A
тар	number of cols of A
mbp	number of cols of b
ic	array of row pointers in the result (this is also computed here again, so that we can have a stand
	alone call of this routine, if for some reason the number of nonzeros in the result is known)
jc	array of column indices in the result c=a*b

Modified by Chensong Zhang on 09/11/2012

Definition at line 51 of file sparse\_util.c.

9.97.2.4 void void fasp\_sparse\_aplbms\_( INT \* ia, INT \* ja, INT \* ib, INT \* jb, INT \* nab, INT \* mab, INT \* ic, INT \* jc)

Addition of two sparse matrices: calculating the nonzero structure of the result if jc is not null. if jc is null only finds num of nonzeroes.

## **Parameters**

ia	array of row pointers 1st summand
ia	array of row pointers 1st summand

ja	array of column indices 1st summand
ib	array of row pointers 2nd summand
jb	array of column indices 2nd summand
nab	number of rows
mab	number of cols
ic	array of row pointers in the result (this is also computed here again, so that we can have a stand
	alone call of this routine, if for some reason the number of nonzeros in the result is known)
jc	array of column indices in the result c=a+b

Definition at line 359 of file sparse\_util.c.

9.97.2.5 void fasp\_sparse\_aplusb\_ ( INT \* 
$$ia$$
, INT \*  $ja$ , REAL \*  $a$ , INT \*  $ib$ , INT \*  $jb$ , REAL \*  $b$ , INT \*  $nab$ , INT \*  $mab$ , INT \*  $ic$ , INT \*  $jc$ , REAL \*  $c$ )

Addition of two sparse matrices: calculating the numerical values in the result.

#### **Parameters**

ia	array of row pointers 1st summand
ja	array of column indices 1st summand
а	entries of the 1st summand
ib	array of row pointers 2nd summand
jb	array of column indices 2nd summand
b	entries of the 2nd summand
nab	number of rows
mab	number of cols
ic	array of row pointers in c=a+b
jc	array of column indices in c=a+b
С	entries of the result: c=a+b

Definition at line 431 of file sparse\_util.c.

9.97.2.6 void fasp\_sparse\_iit\_( INT 
$$*$$
 ia, INT  $*$  ja, INT  $*$  na, INT  $*$  ma, INT  $*$  iat, INT  $*$  jat )

Transpose a boolean matrix (only given by ia, ja)

## **Parameters**

ia	array of row pointers (as usual in CSR)
ja	array of column indices
na	number of rows
ma	number of cols
iat	array of row pointers in the result
jat	array of column indices

### Note

For the concrete algorithm, see:

Definition at line 197 of file sparse\_util.c.

9.97.2.7 ivector fasp\_sparse\_MIS ( dCSRmat \* A )

get the maximal independet set of a CSR matrix

## **Parameters**

Α	pointer to the matrix

#### Note

: only use the sparsity of A, index starts from 1 (fortran)!!

information of A

work space

return

Definition at line 913 of file sparse\_util.c.

9.97.2.8 void fasp\_sparse\_rapcmp\_( INT \* ir, INT \* jr, REAL \* r, INT \* ia, INT \* ja, REAL \* a, INT \* ipt, INT \* jpt, REAL \* pt, INT \* nin, INT \* ncin, INT \* iac, INT \* jac, REAL \* ac, INT \* idummy)

Calculates R\*A\*P after the nonzero structure of the result is known. iac,jac,ac have to be allocated before call to this function.

#### Note

:I: is input :O: is output :IO: is both

#### **Parameters**

ir	:I: array of row pointers for R
jr	:I: array of column indices for R
r	:I: entries of R
ia	:I: array of row pointers for A
ja	:I: array of column indices for A
а	:I: entries of A
ipt	:I: array of row pointers for P
jpt	:I: array of column indices for P
pt	:I: entries of P
nin	:I: number of rows in R
ncin	:I: number of rows in
iac	:O: array of row pointers for P
jac	:O: array of column indices for P
ac	:O: entries of P
idummy	not changed

## Note

compute R\*A\*P for known nonzero structure of the result the result is stored in iac,jac,ac!

Definition at line 791 of file sparse util.c.

9.97.2.9 void fasp\_sparse\_rapms\_ ( INT \* ir, INT \* ir, INT \* ia, INT \* ia, INT \* ip, INT \* ip, INT \* nin, INT \* nin, INT \* nin, INT \* iac, INT \* jac, INT \* maxrout )

Calculates the nonzero structure of R\*A\*P, if jac is not null. If jac is null only finds num of nonzeroes.

#### Note

:I: is input :O: is output :IO: is both

## **Parameters**

ir	:I: array of row pointers for R
jr	:I: array of column indices for R
ia	:I: array of row pointers for A
ja	:I: array of column indices for A
ip	:I: array of row pointers for P
jр	:I: array of column indices for P
nin	:I: number of rows in R
ncin	:I: number of columns in R
iac	:O: array of row pointers for Ac
jac	:O: array of column indices for Ac
maxrout	:O: the maximum nonzeroes per row for R

#### Note

Computes the sparsity pattern of R\*A\*P. maxrout is output and is the maximum nonzeroes per row for r. On output we also have is iac (if jac is null) and jac (if jac entry is not null). R is (n,n) A is (n,n) and P is (n,nc)!

Modified by Chensong Zhang on 09/11/2012

Definition at line 514 of file sparse\_util.c.

9.97.2.10 void fasp\_sparse\_wta\_( INT \* 
$$jw$$
, REAL \*  $w$ , INT \*  $ia$ , INT \*  $ja$ , REAL \*  $a$ , INT \*  $nwp$ , INT \*  $map$ , INT \*  $jv$ , REAL \*  $v$ , INT \*  $nvp$ )

Calculate  $v^{\wedge}t = w^{\wedge}t$  A, where w is a sparse vector and A is sparse matrix. v is an array of dimension = number of columns in A.

Note

:I: is input :O: is output :IO: is both

## **Parameters**

jw	:I: indices such that w[jw] is nonzero
W	:I: the values of w
ia	:I: array of row pointers for A
ja	:I: array of column indices for A
а	:I: entries of A
nwp	:I: number of nonzeroes in w (the length of w)
тар	:I: number of columns in A
jv	:O: indices such that v[jv] is nonzero
V	:O: the result $v^t = w^t A$
nvp	:I: number of nonzeroes in v

Definition at line 651 of file sparse\_util.c.

```
9.97.2.11 void fasp_sparse_wtams_ ( INT * jw, INT * ia, INT * ja, INT * nwp, INT * map, INT * jv, INT * nvp, INT * icp )
```

Finds the nonzeroes in the result of  $v^t = w^t A$ , where w is a sparse vector and A is sparse matrix. jv is an integer array containing the indices of the nonzero elements in the result.

:I: is input :O: is output :IO: is both

## **Parameters**

jw	:I: indices such that w[jw] is nonzero
ia	:I: array of row pointers for A
ja	:I: array of column indices for A
nwp	:I: number of nonzeroes in w (the length of w)
тар	:I: number of columns in A
jv	:O: indices such that v[jv] is nonzero
nvp	:I: number of nonzeroes in v
icp	:IO: is a working array of length (*map) which on output satisfies icp[jv[k]-1]=k; Values of icp[] at
	positions * other than (jv[k]-1) remain unchanged.

Modified by Chensong Zhang on 09/11/2012

Definition at line 598 of file sparse\_util.c.

9.97.2.12 void fasp\_sparse\_ytx\_( INT \* jy, REAL \* y, INT \* jx, REAL \* x, INT \* nyp, INT \* nxp, INT \* icp, REAL \* s)

Calculates  $s = y^{\wedge}t x$ . y is sparse, x is sparse.

note::I: is input::O: is output::IO: is both

#### **Parameters**

jу	:I: indices such that y[jy] is nonzero
у	:I: is a sparse vector.
nyp	:I: number of nonzeroes in y
jx	:I: indices such that x[jx] is nonzero
X	:I: is a sparse vector.
nxp	:I: number of nonzeroes in x
icp	???
s	:O: $s = y^{t} x$ .

Definition at line 736 of file sparse\_util.c.

9.97.2.13 void fasp\_sparse\_ytxbig\_ ( INT \* jy, REAL \* y, INT \* nyp, REAL \* x, REAL \* s)

Calculates  $s = y^{\wedge}t x$ . y-sparse, x - no.

Note

:I: is input :O: is output :IO: is both

## **Parameters**

jy	:I: indices such that y[jy] is nonzero
у	:I: is a sparse vector.
nyp	:I: number of nonzeroes in v
X	:I: also a vector assumed to have entry for any j=jy[i]-1; for i=1:nyp. This means that x here does
	not have to be sparse.

```
s :0: s = y^t x.
```

Definition at line 702 of file sparse\_util.c.

# 9.98 spbcgs.c File Reference

Krylov subspace methods - Preconditioned BiCGstab with safe net.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

#### **Functions**

 INT fasp\_solver\_dcsr\_spbcgs (dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned BiCGstab method for solving Au=b with safe net.

 INT fasp\_solver\_dbsr\_spbcgs (dBSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned BiCGstab method for solving Au=b with safe net.

 INT fasp\_solver\_bdcsr\_spbcgs (block\_dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned BiCGstab method for solving Au=b with safe net.

 INT fasp\_solver\_dstr\_spbcgs (dSTRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop type, const SHORT print level)

Preconditioned BiCGstab method for solving Au=b with safe net.

## 9.98.1 Detailed Description

Krylov subspace methods - Preconditioned BiCGstab with safe net. Abstract algorithm

PBICGStab method to solve A\*x=b is to generate  $\{x \mid k\}$  to approximate x

Note: We generate a series of  $\{p_k\}$  such that  $V_k=\text{span}\{p_1,...,p_k\}$ .

```
Step 0. Given A, b, x 0, M
```

Step 1. Compute residual  $r_0 = b-A*x_0$  and convergence check;

```
Step 2. Initialization z_0 = M^{(-1)}*r_0, p_0=z_0;
```

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r k,z k,p k);
- update solution: x\_{k+1} = x\_k + alpha\*p\_k;
- · check whether x is NAN:
- · perform stagnation check;

- update residual: r\_{k+1} = r\_k alpha\*(A\*p\_k);
- if  $r_{k+1} < r_{best}$ : save  $x_{k+1}$  as  $x_{best}$ ;
- · perform residual check;
- obtain p\_{k+1} using {p\_0, p\_1, ..., p\_k};
- · prepare for next iteration;
- · print the result of k-th iteration; END FOR

Convergence check: norm(r)/norm(b) < tol

Stagnation check:

- IF  $norm(alpha*p_k)/norm(x_{k+1}) < tol_stag$ 
  - 1. compute  $r=b-A*x \{k+1\}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Stag\_Check ) restart;
- END IF

Residual check:

- IF  $norm(r_{k+1})/norm(b) < tol$ 
  - 1. compute the real residual  $r = b-A*x_{k+1}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Res\_Check ) restart;
- END IF

Safe net check:

- IF  $r_{k+1} > r_{best}$ 
  - 1.  $x_{k+1} = x_{best}$
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See spbcgs.c for a safer version

Definition in file spbcgs.c.

## 9.98.2 Function Documentation

9.98.2.1 INT fasp\_solver\_bdcsr\_spbcgs ( block\_dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned BiCGstab method for solving Au=b with safe net.

## **Parameters**

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

## **Author**

Chensong Zhang

Date

03/31/2013

Definition at line 868 of file spbcgs.c.

9.98.2.2 INT fasp\_solver\_dbsr\_spbcgs ( dBSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned BiCGstab method for solving Au=b with safe net.

## **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

## Returns

Number of iterations if converged, error message otherwise

## **Author**

Chensong Zhang

Date

03/31/2013

Definition at line 480 of file spbcgs.c.

9.98.2.3 INT fasp\_solver\_dcsr\_spbcgs ( dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned BiCGstab method for solving Au=b with safe net.

## **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

**Author** 

Chensong Zhang

Date

03/31/2013

Definition at line 92 of file spbcgs.c.

9.98.2.4 INT fasp\_solver\_dstr\_spbcgs ( dSTRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned BiCGstab method for solving Au=b with safe net.

## **Parameters**

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

## Returns

Number of iterations if converged, error message otherwise

**Author** 

Chensong Zhang

Date

03/31/2013

Definition at line 1256 of file spbcgs.c.

# 9.99 spcg.c File Reference

Krylov subspace methods – Preconditioned conjugate gradient with safe net.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

#### **Functions**

INT fasp\_solver\_dcsr\_spcg (dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned conjugate gradient method for solving Au=b with safe net.

• INT fasp\_solver\_bdcsr\_spcg (block\_dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned conjugate gradient method for solving Au=b with safe net.

INT fasp\_solver\_dstr\_spcg (dSTRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

Preconditioned conjugate gradient method for solving Au=b with safe net.

## 9.99.1 Detailed Description

Krylov subspace methods – Preconditioned conjugate gradient with safe net. Abstract algorithm

PCG method to solve A\*x=b is to generate  $\{x\_k\}$  to approximate x

```
Step 0. Given A, b, x_0, M
```

Step 1. Compute residual  $r_0 = b-A*x_0$  and convergence check;

```
Step 2. Initialization z 0 = M^{-1}*r 0, p 0=z 0;
```

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r\_k,z\_k,p\_k);
- update solution: x\_{k+1} = x\_k + alpha\*p\_k;
- · check whether x is NAN;
- · perform stagnation check;
- update residual:  $r_{k+1} = r_k alpha*(A*p_k)$ ;
- if r\_{k+1} < r\_{best}: save x\_{k+1} as x\_{best};
- · perform residual check;
- obtain p\_{k+1} using {p\_0, p\_1, ..., p\_k};
- · prepare for next iteration;
- print the result of k-th iteration; END FOR

Convergence check: norm(r)/norm(b) < tol

Stagnation check:

- IF norm(alpha\*p\_k)/norm(x\_{k+1}) < tol\_stag</li>
  - 1. compute  $r=b-A*x_{k+1}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Stag\_Check ) restart;
- END IF

## Residual check:

- IF  $norm(r_{k+1})/norm(b) < tol$ 
  - 1. compute the real residual  $r = b-A*x_{k+1}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Res\_Check ) restart;
- END IF

Safe net check:

- IF  $r_{k+1} > r_{best}$ 
  - 1.  $x_{k+1} = x_{best}$
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See pcg.c for a version without safe net

Definition in file spcg.c.

## 9.99.2 Function Documentation

9.99.2.1 INT fasp\_solver\_bdcsr\_spcg ( block\_dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned conjugate gradient method for solving Au=b with safe net.

#### **Parameters**

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)

tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

#### **Returns**

Number of iterations if converged, error message otherwise

#### **Author**

Chensong Zhang

Date

03/28/2013

Definition at line 414 of file spcg.c.

9.99.2.2 INT fasp\_solver\_dcsr\_spcg ( dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned conjugate gradient method for solving Au=b with safe net.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

## Returns

Number of iterations if converged, error message otherwise

#### **Author**

Chensong Zhang

Date

03/28/2013

Definition at line 89 of file spcg.c.

9.99.2.3 INT fasp\_solver\_dstr\_spcg ( dSTRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

Preconditioned conjugate gradient method for solving Au=b with safe net.

#### **Parameters**

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
MaxIt	Maximal number of iterations
tol	Tolerance for stopping
рс	Pointer to the structure of precondition (precond)
print_level	How much information to print out
stop_type	Stopping criteria type

#### Returns

Number of iterations if converged, error message otherwise

#### **Author**

Chensong Zhang

Date

03/28/2013

Definition at line 738 of file spcg.c.

# 9.100 spgmres.c File Reference

Krylov subspace methods - Preconditioned GMRes with safe net.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

## **Functions**

 INT fasp\_solver\_dcsr\_spgmres (dCSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Preconditioned GMRES method for solving Au=b with safe-guard.

 INT fasp\_solver\_bdcsr\_spgmres (block\_dCSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Preconditioned GMRES method for solving Au=b with safe-guard.

 INT fasp\_solver\_dbsr\_spgmres (dBSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Preconditioned GMRES method for solving Au=b with safe-guard.

• INT fasp\_solver\_dstr\_spgmres (dSTRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Preconditioned GMRES method for solving Au=b with safe-guard.

## 9.100.1 Detailed Description

Krylov subspace methods - Preconditioned GMRes with safe net.

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See also pgmres.c for a variable restarting version. See pgmres.c for a version without safe net

Definition in file spgmres.c.

## 9.100.2 Function Documentation

9.100.2.1 INT fasp\_solver\_bdcsr\_spgmres ( block\_dCSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Preconditioned GMRES method for solving Au=b with safe-guard.

#### **Parameters**

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/05/2013

Definition at line 387 of file spgmres.c.

9.100.2.2 INT fasp\_solver\_dbsr\_spgmres ( dBSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Preconditioned GMRES method for solving Au=b with safe-guard.

## **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

#### **Author**

Chensong Zhang

Date

04/05/2013

Definition at line 728 of file spgmres.c.

9.100.2.3 INT fasp\_solver\_dcsr\_spgmres ( dCSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Preconditioned GMRES method for solving Au=b with safe-guard.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

## **Author**

Chensong Zhang

#### Date

04/05/2013 Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate

Definition at line 46 of file spgmres.c.

9.100.2.4 INT fasp\_solver\_dstr\_spgmres ( dSTRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop type, const SHORT print level )

Preconditioned GMRES method for solving Au=b with safe-guard.

#### **Parameters**

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

#### **Author**

Chensong Zhang

Date

04/05/2013

Definition at line 1069 of file spgmres.c.

## 9.101 spminres.c File Reference

Krylov subspace methods - Preconditioned minimal residual with safe net.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

## **Functions**

• INT fasp\_solver\_dcsr\_spminres (dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

A preconditioned minimal residual (Minres) method for solving Au=b with safe net.

• INT fasp\_solver\_bdcsr\_spminres (block\_dCSRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop type, const SHORT print level)

A preconditioned minimal residual (Minres) method for solving Au=b with safe net.

 INT fasp\_solver\_dstr\_spminres (dSTRmat \*A, dvector \*b, dvector \*u, precond \*pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level)

A preconditioned minimal residual (Minres) method for solving Au=b with safe net.

## 9.101.1 Detailed Description

Krylov subspace methods - Preconditioned minimal residual with safe net. Abstract algorithm

 $\textit{Krylov method to solve A} * x = b \textit{ is to generate } \{x\_k\} \textit{ to approximate } x, \textit{ where } x\_k \textit{ is the optimal solution in Krylov space } x = b \textit{ is to generate } \{x\_k\} \textit{ to approximate } x, \textit{ where } x\_k \textit{ is the optimal solution in Krylov space } x = b \textit{ is to generate } \{x\_k\} \textit{ to approximate } x, \textit{ where } x\_k \textit{ is the optimal solution } x = b \textit{ is to generate } \{x\_k\} \textit{ to approximate } x, \textit{ where } x\_k \textit{ is the optimal solution } x = b \textit{ is to generate } \{x\_k\} \textit{ to approximate } x, \textit{ where } x\_k \textit{ is the optimal solution } x = b \textit{ is to generate } \{x\_k\} \textit{ to approximate } x, \textit{ where } x\_k \textit{ is the optimal solution } x = b \textit{ is the optima$ 

```
V_k=span\{r_0,A*r_0,A^2*r_0,...,A^{k-1}*r_0\},
```

under some inner product.

For the implementation, we generate a series of {p\_k} such that V\_k=span{p\_1,...,p\_k}. Details:

- Step 0. Given A, b, x 0, M
- Step 1. Compute residual  $r_0 = b-A*x_0$  and convergence check;
- Step 2. Initialization  $z_0 = M^{-1}*r_0$ ,  $p_0=z_0$ ;
- Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r k,z k,p k);
- update solution: x\_{k+1} = x\_k + alpha\*p\_k;
- check whether x is NAN;
- · perform stagnation check;
- update residual: r\_{k+1} = r\_k alpha\*(A\*p\_k);
- if r\_{k+1} < r\_{best}: save x\_{k+1} as x\_{best};
- · perform residual check;
- obtain p\_{k+1} using {p\_0, p\_1, ..., p\_k};
- · prepare for next iteration;
- · print the result of k-th iteration; END FOR

Convergence check: norm(r)/norm(b) < tol

Stagnation check:

- IF norm(alpha\*p\_k)/norm(x\_{k+1}) < tol\_stag</li>
  - 1. compute  $r=b-A*x_{k+1}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Stag\_Check ) restart;
- END IF

Residual check:

- IF  $norm(r_{k+1})/norm(b) < tol$ 
  - 1. compute the real residual  $r = b-A*x \{k+1\}$ ;
  - 2. convergence check;
  - 3. IF ( not converged & restart\_number < Max\_Res\_Check ) restart;

• END IF

Safe net check:

• IF 
$$r_{k+1} > r_{best}$$

1. 
$$x_{k+1} = x_{best}$$

• END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See pminres.c for a version without safe net

Definition in file spminres.c.

## 9.101.2 Function Documentation

9.101.2.1 INT fasp\_solver\_bdcsr\_spminres ( block\_dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

A preconditioned minimal residual (Minres) method for solving Au=b with safe net.

#### **Parameters**

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

## Returns

Number of iterations if converged, error message otherwise

**Author** 

Chensong Zhang

Date

04/09/2013

Definition at line 543 of file spminres.c.

9.101.2.2 INT fasp\_solver\_dcsr\_spminres ( dCSRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

A preconditioned minimal residual (Minres) method for solving Au=b with safe net.

## **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

#### Returns

Number of iterations if converged, error message otherwise

## **Author**

Chensong Zhang

Date

04/09/2013

Definition at line 96 of file spminres.c.

9.101.2.3 INT fasp\_solver\_dstr\_spminres ( dSTRmat \* A, dvector \* b, dvector \* u, precond \* pc, const REAL tol, const INT MaxIt, const SHORT stop\_type, const SHORT print\_level )

A preconditioned minimal residual (Minres) method for solving Au=b with safe net.

## **Parameters**

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
MaxIt	Maximal number of iterations
tol	Tolerance for stopping
рс	Pointer to the structure of precondition (precond)
print_level	How much information to print out
stop_type	Stopping criteria type

## Returns

Number of iterations if converged, error message otherwise

## **Author**

Chensong Zhang

Date

04/09/2013

Definition at line 990 of file spminres.c.

## 9.102 spvgmres.c File Reference

Krylov subspace methods - Preconditioned variable-restart GMRes with safe net.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

#### **Functions**

 INT fasp\_solver\_dcsr\_spvgmres (dCSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

INT fasp\_solver\_bdcsr\_spvgmres (block\_dCSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Preconditioned GMRES method for solving Au=b.

 INT fasp\_solver\_dbsr\_spvgmres (dBSRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

 INT fasp\_solver\_dstr\_spvgmres (dSTRmat \*A, dvector \*b, dvector \*x, precond \*pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

#### 9.102.1 Detailed Description

Krylov subspace methods - Preconditioned variable-restart GMRes with safe net.

Note

Refer to A.H. Baker, E.R. Jessup, and Tz.V. Kolev A Simple Strategy for Varying the Restart Parameter in GMRE-S(m) Journal of Computational and Applied Mathematics, 230 (2009) pp. 751-761. UCRL-JRNL-235266. See pygmres.c a version without safe net

Definition in file spvgmres.c.

## 9.102.2 Function Documentation

9.102.2.1 INT fasp\_solver\_bdcsr\_spvgmres ( block\_dCSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Preconditioned GMRES method for solving Au=b.

## **Parameters**

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

## Returns

Number of iterations if converged, error message otherwise

## **Author**

Chensong Zhang

Date

04/06/2013

Definition at line 427 of file spygmres.c.

9.102.2.2 INT fasp\_solver\_dbsr\_spvgmres ( dBSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

#### **Parameters**

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

## Returns

Number of iterations if converged, error message otherwise

## **Author**

Chensong Zhang

Date

04/06/2013

Definition at line 807 of file spvgmres.c.

9.102.2.3 INT fasp\_solver\_dcsr\_spvgmres ( dCSRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

#### **Parameters**

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

#### **Returns**

Number of iterations if converged, error message otherwise

## **Author**

Chensong Zhang

#### Date

04/06/2013 Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate

Definition at line 49 of file spvgmres.c.

9.102.2.4 INT fasp\_solver\_dstr\_spvgmres ( dSTRmat \* A, dvector \* b, dvector \* x, precond \* pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop\_type, const SHORT print\_level )

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

#### **Parameters**

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type

pri	nt level	How much information to print	out

#### Returns

Number of iterations if converged, error message otherwise

#### **Author**

Chensong Zhang

#### Date

04/06/2013

Definition at line 1187 of file spvgmres.c.

## 9.103 threads.c File Reference

Get and set number of threads and assigne work load for each thread.

```
#include <stdio.h>
#include <stdlib.h>
#include "fasp.h"
```

## **Functions**

• void FASP\_GET\_START\_END (INT procid, INT nprocs, INT n, INT \*start, INT \*end)

Assign Load to each thread.

## 9.103.1 Detailed Description

Get and set number of threads and assigne work load for each thread.

Definition in file threads.c.

## 9.103.2 Function Documentation

```
9.103.2.1 void FASP_GET_START_END ( INT procid, INT nprocs, INT n, INT * start, INT * end )
```

Assign Load to each thread.

#### **Parameters**

procid	Index of thread
nprocs	Number of threads

n	Total workload
start	Pointer to the begin of each thread in total workload
end	Pointer to the end of each thread in total workload

#### **Author**

Chunsheng Feng, Xiaoqiang Yue and Zheng Li

Date

June/25/2012

Definition at line 83 of file threads.c.

# 9.104 timing.c File Reference

## Timing subroutines.

```
#include <time.h>
#include "fasp_functs.h"
#include "fasp.h"
```

## **Functions**

void fasp\_gettime (REAL \*time)
 Get system time.

## 9.104.1 Detailed Description

Timing subroutines.

Definition in file timing.c.

## 9.104.2 Function Documentation

```
9.104.2.1 fasp_gettime ( REAL * time )
```

Get system time.

**Author** 

Chunsheng Feng, Zheng LI

Date

11/10/2012

Definition at line 28 of file timing.c.

## 9.105 vec.c File Reference

Simple operations for vectors.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

## **Functions**

INT fasp dvec isnan (dvector \*u)

Check a dvector whether there is NAN.

dvector fasp dvec create (const INT m)

Create dvector data space of REAL type.

ivector fasp\_ivec\_create (const INT m)

Create vector data space of INT type.

void fasp\_dvec\_alloc (const INT m, dvector \*u)

Create dvector data space of REAL type.

void fasp ivec alloc (const INT m, ivector \*u)

Create vector data space of INT type.

void fasp\_dvec\_free (dvector \*u)

Free vector data space of REAL type.

void fasp\_ivec\_free (ivector \*u)

Free vector data space of INT type.

void fasp\_dvec\_null (dvector \*x)

Initialize dvector.

void fasp dvec rand (const INT n, dvector \*x)

Generate random REAL vector in the range from 0 to 1.

void fasp\_dvec\_set (INT n, dvector \*x, REAL val)

Initialize dvector x[i]=val for i=0:n-1.

void fasp\_ivec\_set (const INT m, ivector \*u)

Set ivector value to be m.

void fasp\_dvec\_cp (dvector \*x, dvector \*y)

Copy dvector x to dvector y.

REAL fasp\_dvec\_maxdiff (dvector \*x, dvector \*y)

Maximal difference of two dvector x and y.

void fasp\_dvec\_symdiagscale (dvector \*b, dvector \*diag)

Symmetric diagonal scaling  $D^{\wedge}$  {-1/2}b.

## 9.105.1 Detailed Description

Simple operations for vectors.

Note

Every structures should be initialized before usage.

Definition in file vec.c.

9.105 vec.c File Reference 413

## 9.105.2 Function Documentation

9.105.2.1 void fasp\_dvec\_alloc ( const INT m, dvector \*u )

Create dvector data space of REAL type.

**Parameters** 

ſ	т	Number of rows
	и	Pointer to dvector (OUTPUT)

**Author** 

Chensong Zhang

Date

2010/04/06

Definition at line 99 of file vec.c.

9.105.2.2 void fasp\_dvec\_cp ( dvector \* x, dvector \* y )

Copy dvector x to dvector y.

**Parameters** 

X	Pointer to dvector
У	Pointer to dvector (MODIFIED)

**Author** 

Chensong Zhang

Date

11/16/2009

Definition at line 345 of file vec.c.

9.105.2.3 dvector fasp\_dvec\_create ( const INT m )

Create dvector data space of REAL type.

**Parameters** 

m	Number of rows

Returns

u The new dvector

**Author** Chensong Zhang Date 2010/04/06 Definition at line 56 of file vec.c. 9.105.2.4 void fasp\_dvec\_free ( dvector \* u ) Free vector data space of REAL type. **Parameters** Pointer to dvector which needs to be deallocated **Author** Chensong Zhang Date 2010/04/03 Definition at line 139 of file vec.c. 9.105.2.5 INT fasp\_dvec\_isnan ( dvector \* u ) Check a dvector whether there is NAN. **Parameters** Pointer to dvector Returns Return TRUE if there is NAN **Author** Chensong Zhang Date 2013/03/31

Definition at line 33 of file vec.c.

Maximal difference of two dvector x and y.

9.105.2.6 REAL fasp\_dvec\_maxdiff ( dvector \* x, dvector \* y )

Generated on Mon Sep 30 2013 14:49:54 for Fast Auxiliary Space Preconditioning by Doxygen

9.105 vec.c File Reference 415

## **Parameters**

Х	Pointer to dvector
у	Pointer to dvector

Returns

Maximal norm of x-y

Author

Chensong Zhang

Date

11/16/2009

Modified by chunsheng Feng, Zheng Li

Date

06/30/2012

Definition at line 368 of file vec.c.

9.105.2.7 void fasp\_dvec\_null ( dvector \* x )

Initialize dvector.

**Parameters** 

ſ	X	Pointer to dvector which needs to be initialized

**Author** 

Chensong Zhang

Date

2010/04/03

Definition at line 177 of file vec.c.

9.105.2.8 void fasp\_dvec\_rand ( const INT n, dvector \* x )

Generate random REAL vector in the range from 0 to 1.

**Parameters** 

n	Size of the vector
X	Pointer to dvector

## Note

Sample usage:

dvector xapp;

fasp\_dvec\_create(100,&xapp);

fasp\_dvec\_rand(100,&xapp);

fasp\_dvec\_print(100,&xapp);

## Author

Chensong Zhang

Date

11/16/2009

Definition at line 203 of file vec.c.

9.105.2.9 void fasp\_dvec\_set ( INT n, dvector \* x, REAL val )

Initialize dvector x[i]=val for i=0:n-1.

#### **Parameters**

n	Number of variables
X	Pointer to dvector
val	Initial value for the vector

## **Author**

Chensong Zhang

Date

11/16/2009

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 235 of file vec.c.

9.105.2.10 void fasp\_dvec\_symdiagscale ( dvector \* b, dvector \* diag )

Symmetric diagonal scaling  $D^{-1/2}b$ .

9.105 vec.c File Reference 417

## **Parameters**

b	Pointer to dvector
diag	Pointer to dvector: the diagonal entries

**Author** 

Xiaozhe Hu

Date

01/31/2011

Definition at line 421 of file vec.c.

9.105.2.11 void fasp\_ivec\_alloc ( const INT m, ivector \*u)

Create vector data space of INT type.

## **Parameters**

m	Number of rows
и	Pointer to ivector (OUTPUT)

**Author** 

Chensong Zhang

Date

2010/04/06

Definition at line 119 of file vec.c.

9.105.2.12 ivector fasp\_ivec\_create ( const INT m )

Create vector data space of INT type.

**Parameters** 

m	Number of rows
---	----------------

Returns

u The new ivector

**Author** 

Chensong Zhang

Date

2010/04/06

Definition at line 78 of file vec.c.

9.105.2.13 void fasp\_ivec\_free ( ivector \*u )

Free vector data space of INT type.

## **Parameters**

и	Pointer to ivector which needs to be deallocated
---	--

## **Author**

Chensong Zhang

Date

2010/04/03

Note

This function is same as fasp\_dvec\_free except input type.

Definition at line 159 of file vec.c.

```
9.105.2.14 void fasp_ivec_set ( const INT m, ivector * u )
```

Set ivector value to be m.

#### **Parameters**

т	Integer value of ivector
и	Pointer to ivector (MODIFIED)

## Author

Chensong Zhang

Date

04/03/2010

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 304 of file vec.c.

# 9.106 wrapper.c File Reference

Wrappers for accessing functions by advanced users.

```
#include "fasp.h"
#include "fasp_block.h"
#include "fasp_functs.h"
```

## **Functions**

void fasp\_fwrapper\_amg\_ (INT \*n, INT \*nnz, INT \*ia, INT \*ja, REAL \*a, REAL \*b, REAL \*u, REAL \*tol, INT \*maxit, INT \*ptrlvl)

Solve Ax=b by Ruge and Stuben's classic AMG.

void fasp\_fwrapper\_krylov\_amg\_ (INT \*n, INT \*nnz, INT \*ia, INT \*ja, REAL \*a, REAL \*b, REAL \*u, REAL \*tol, INT \*maxit, INT \*ptrlvl)

Solve Ax=b by Krylov method preconditioned by classic AMG.

INT fasp\_wrapper\_dbsr\_krylov\_amg (INT n, INT nnz, INT nb, INT \*ia, INT \*ja, REAL \*a, REAL \*b, REAL \*u, REAL tol, INT maxit, INT ptrlvl)

Solve Ax=b by Krylov method preconditioned by AMG (dcsr - > dbsr)

INT fasp\_wrapper\_dcoo\_dbsr\_krylov\_amg (INT n, INT nnz, INT nb, INT \*ia, INT \*ja, REAL \*a, REAL \*b, REAL
 \*u, REAL tol, INT maxit, INT ptrlvl)

Solve Ax=b by Krylov method preconditioned by AMG (dcoo - > dbsr)

## 9.106.1 Detailed Description

Wrappers for accessing functions by advanced users.

Note

Input variables should not need fasp.h!!!

Definition in file wrapper.c.

## 9.106.2 Function Documentation

9.106.2.1 void void fasp\_fwrapper\_amg\_ ( INT \* n, INT \* n, INT \* ia, INT \* ja, REAL \* a, REAL \* b, REAL \* u, REAL \* tol, INT \* maxit, INT \* ptrlvl )

Solve Ax=b by Ruge and Stuben's classic AMG.

#### **Parameters**

n	Number of cols of A
nnz	Number of nonzeros of A
ia	IA of A in CSR format
ja	JA of A in CSR format
а	VAL of A in CSR format
b	RHS vector
и	Solution vector
tol	Tolerance for iterative solvers
maxit	Max num of iterations
ptrlvl	Print level for iterative solvers

#### **Author**

Chensong Zhang

Date

09/16/2010

Definition at line 37 of file wrapper.c.

9.106.2.2 void fasp\_fwrapper\_krylov\_amg\_ ( INT \* n, INT \* n, INT \* ia, INT \* ja, REAL \* a, REAL \* b, REAL \* u, REAL \* u,

Solve Ax=b by Krylov method preconditioned by classic AMG.

#### **Parameters**

n	Number of cols of A
nnz	Number of nonzeros of A
ia	IA of A in CSR format
ja	JA of A in CSR format
а	VAL of A in CSR format
b	RHS vector
и	Solution vector
tol	Tolerance for iterative solvers
maxit	Max num of iterations
ptrlvl	Print level for iterative solvers

**Author** 

Chensong Zhang

Date

09/16/2010

Definition at line 87 of file wrapper.c.

9.106.2.3 INT fasp\_wrapper\_dbsr\_krylov\_amg ( INT n, INT n), INT n, INT n, INT n, INT n), INT n, REAL n0, REAL n0, REAL n0, INT n0, IN

Solve Ax=b by Krylov method preconditioned by AMG (dcsr - > dbsr)

#### **Parameters**

n	Number of cols of A
nnz	Number of nonzeros of A
nb	Size of each small block
ia	IA of A in CSR format
ja	JA of A in CSR format
а	VAL of A in CSR format
b	RHS vector
и	Solution vector
tol	Tolerance for iterative solvers
maxit	Max num of iterations
ptrlvl	Print level for iterative solvers

**Author** 

Xiaozhe Hu

Date

03/05/2013

Definition at line 142 of file wrapper.c.

9.106.2.4 INT fasp\_wrapper\_dcoo\_dbsr\_krylov\_amg ( INT n, INT n, INT nb, INT \* ia, INT \* ia, REAL \* a, REAL \*

Solve Ax=b by Krylov method preconditioned by AMG (dcoo - > dbsr)

## **Parameters**

n	Number of cols of A
nnz	Number of nonzeros of A
nb	Size of each small block
ia	IA of A in COO format
ja	JA of A in COO format
а	VAL of A in COO format
b	RHS vector
и	Solution vector
tol	Tolerance for iterative solvers
maxit	Max num of iterations
ptrlvl	Print level for iterative solvers

Author

Xiaozhe Hu

Date

03/06/2013

Definition at line 226 of file wrapper.c.

# Index

FASP_HEADER	input_param, 41
fasp.h, 144	AMG_schwarz_levels
	input_param, 41
A	AMG_smooth_filter
precond_block_data, 48	input_param, 41
precond_FASP_blkoil_data, 59	AMG_smooth_order
ABS	input_param, 41
fasp.h, 144	AMG_smoother
AMG_ILU_levels	input param, 41
input_param, 39	AMG_strong_coupled
AMG_aggressive_level	input_param, 41
input_param, 39	AMG strong threshold
AMG_aggressive_path	input_param, 41
input_param, 39	AMG tentative smooth
AMG_amli_degree	input_param, 41
input_param, 39	AMG tol
AMG_coarse_dof	input param, 41
input_param, 39	AMG truncation threshold
AMG_coarse_scaling	input param, 42
input_param, 39	. —
AMG_coarsening_type	AMG_type
input_param, 39	input_param, 42
AMG_cycle_type	AMLI_CYCLE
input_param, 39	messages.h, 236
AMG_data, 19	ASCEND
AMG_data_bsr, 20	messages.h, 236
AMG_interpolation_type	Aarray
input_param, 40	precond_block_data, 48
AMG_levels	Ablock
input_param, 40	precond_block_data, 48
AMG_max_aggregation	amg.c, 65
input_param, 40	fasp_solver_amg, 65
AMG_max_row_sum	amg_setup_aggregation_bsr.inl, 66
input_param, 40	amg_setup_aggregation_csr.inl, 66
AMG_maxit	amg_setup_cr.c, 66
input_param, 40	fasp_amg_setup_cr, 67
AMG_nl_amli_krylov_type	amg_setup_rs.c, 67
input_param, 40	fasp_amg_setup_rs, 68
AMG_param, 21	fasp_amg_setup_rs_omp, 68
AMG_polynomial_degree	amg_setup_sa.c, 69
input_param, 40	fasp_amg_setup_sa, 69
AMG_postsmooth_iter	amg_setup_ua.c, 70
input_param, 40	fasp_amg_setup_ua, 71
AMG_presmooth_iter	fasp_amg_setup_ua_bsr, 71
input_param, 40	amg_solve.c, 71
AMG relaxation	fasp amg solve, 72

fasp_amg_solve_amli		fasp_blas_dcsr_rap_agg1, 100
fasp_amg_solve_nl_a		fasp_blas_dcsr_vmv, 101
fasp_famg_solve, 73	b	las_csrl.c, 101
amgparam		fasp_blas_dcsrl_mxv, 102
precond_block_data, 4	<del>1</del> 9 b	las_smat.c, 102
amlirecur.c, 74	75	fasp_blas_array_axpy_nc2, 104
fasp_amg_amli_coef,	75	fasp_blas_array_axpy_nc3, 104
fasp_solver_amli, 76	70	fasp_blas_array_axpy_nc5, 105
fasp_solver_nl_amli, 7		fasp_blas_array_axpy_nc7, 105
fasp_solver_nl_amli_b	osr, 77	fasp_blas_array_axpyz_nc2, 105
array.c, 77		fasp_blas_array_axpyz_nc3, 106
fasp_array_cp, 78	0	fasp_blas_array_axpyz_nc5, 106
fasp_array_cp_nc3, 78		fasp_blas_array_axpyz_nc7, 107
fasp_array_cp_nc5, 79		fasp_blas_smat_aAxpby, 107
fasp_array_cp_nc7, 79	3	fasp_blas_smat_mul, 108
fasp_array_null, 79		fasp_blas_smat_mul_nc2, 108
fasp_array_set, 80 fasp_iarray_cp, 80		fasp_blas_smat_mul_nc3, 109
fasp_iarray_cp, 80		fasp_blas_smat_mul_nc5, 109
iasp_iarray_set, or		fasp_blas_smat_mul_nc7, 109 fasp_blas_smat_mxv, 110
BIGREAL		fasp_blas_smat_mxv_nc2, 110
fasp.h, 144		fasp_blas_smat_mxv_nc3, 110
blas_array.c, 81		fasp blas smat mxv nc5, 112
fasp_blas_array_ax, 8	2	fasp_blas_smat_mxv_nc7, 112
fasp_blas_array_axpb		fasp_blas_smat_ymAx, 112
fasp_blas_array_axpy	-	fasp_blas_smat_ymAx_nc2, 114
fasp_blas_array_axpy		fasp_blas_smat_ymAx_nc3, 114
fasp_blas_array_dotpr		fasp_blas_smat_ymAx_nc5, 115
fasp_blas_array_norm		fasp_blas_smat_ymAx_nc7, 115
fasp_blas_array_norm		fasp_blas_smat_ymAx_ns, 116
fasp_blas_array_norm		fasp_blas_smat_ymAx_ns2, 116
blas_bcsr.c, 86	, <del>00</del>	fasp_blas_smat_ymAx_ns3, 117
fasp_blas_bdbsr_aAxp	nv 87	fasp_blas_smat_ymAx_ns5, 117
fasp_blas_bdbsr_mxv	· <del>-</del>	fasp_blas_smat_ymAx_ns7, 118
fasp_blas_bdcsr_aAxp		fasp_blas_smat_ypAx, 118
fasp blas bdcsr mxv.	· ·	fasp_blas_smat_ypAx_nc2, 119
blas bsr.c, 89	, 00	fasp_blas_smat_ypAx_nc3, 119
fasp_blas_dbsr_aAxpl	ov 90	fasp_blas_smat_ypAx_nc5, 119
fasp_blas_dbsr_aAxpy		fasp_blas_smat_ypAx_nc7, 121
fasp_blas_dbsr_mxv,		las_str.c, 121
fasp_blas_dbsr_rap, 9		fasp_blas_dstr_aAxpy, 122
fasp_blas_dbsr_rap1,		fasp_blas_dstr_mxv, 122
blas_csr.c, 94		fasp_dstr_diagscale, 122
fasp_blas_dcsr_aAxpy	v. 95 b	las_vec.c, 123
fasp_blas_dcsr_aAxpy		fasp blas dvec axpy, 124
fasp_blas_dcsr_add,		fasp_blas_dvec_axpyz, 124
fasp_blas_dcsr_axm,		fasp_blas_dvec_dotprod, 124
fasp_blas_dcsr_mxm,		fasp_blas_dvec_norm1, 125
fasp_blas_dcsr_mxv,		fasp_blas_dvec_norm2, 125
fasp_blas_dcsr_mxv_a		fasp_blas_dvec_norminf, 126
fasp_blas_dcsr_ptap,		fasp_blas_dvec_relerr, 126
fasp_blas_dcsr_rap, 9		lock_BSR, 23
fasp_blas_dcsr_rap4,		fasp_block.h, 151
fasp_blas_dcsr_rap_a		lock_Reservoir, 26

fasp_block.h, 152	fasp.h, 148
block_dCSRmat, 24	dCSRmat, 29
fasp_block.h, 151	fasp.h, 148
block_dvector, 25	dCSRmat2SAMGInput
fasp_block.h, 151	interface_samg.c, 177
block_iCSRmat, 25	DEBUG MODE
fasp_block.h, 152	fasp.h, 145
block_ivector, 26	DESCEND
fasp_block.h, 152	messages.h, 237
1- /	DIAGONAL_PREF
C2N	fasp.h, 145
fasp.h, 144	DLMALLOC
CF_ORDER	fasp.h, 145
messages.h, 236	dSTRmat, 31
CGPT	fasp.h, 148
messages.h, 236	ddenmat, 30
CHMEM_MODE	fasp.h, 148
fasp.h, 145	diag
CLASSIC_AMG	_
messages.h, 237	precond_block_reservoir_data, 51
COARSE AC	diaginv
messages.h, 237	precond_block_reservoir_data, 51
COARSE CR	precond_FASP_blkoil_data, 59
messages.h, 237	diaginv_S
COARSE RS	precond_FASP_blkoil_data, 60
messages.h, 237	diaginv_noscale
CPFIRST	precond_FASP_blkoil_data, 60
messages.h, 237	diaginvS
checkmat.c, 127	precond_block_reservoir_data, 51
fasp_check_dCSRmat, 128	doxygen.h, 139
fasp_check_diagdom, 128	dvector, 31
fasp_check_diagpos, 128	fasp.h, 148
fasp_check_diagzero, 130	dvector2SAMGInput
fasp check iCSRmat, 130	interface_samg.c, 177
fasp_check_symm, 130	
coarsening cr.c, 132	е
fasp_amg_coarsening_cr, 132	grid2d, 33
coarsening_rs.c, 133	ERROR_ALLOC_MEM
fasp amg coarsening rs, 134	messages.h, 237
col idx	ERROR_AMG_COARSEING
precond_block_data, 49	messages.h, 238
convert.c, 135	ERROR_DATA_ZERODIAG
endian convert int, 136	messages.h, 238
endian_convert_real, 136	ERROR DUMMY VAR
fasp_aux_bbyteToldouble, 136	messages.h, 238
• — •	ERROR_INPUT_PAR
fasp_aux_change_endian4, 138	messages.h, 238
fasp_aux_change_endian8, 138	ERROR MISC
dBSRmat, 27	messages.h, 238
fasp_block.h, 152	ERROR NUM BLOCKS
JA, 27	messages.h, 238
val, 27	ERROR_OPEN_FILE
dCOOmat, 28	messages.h, 239
fasp.h, 148	ERROR QUAD DIM
dCSRLmat, 29	messages.h, 239
door Linut, Lo	111000ag00.11, 200

ERROR_QUAD_TYPE	DIAGONAL_PREF, 145
messages.h, 239	DLMALLOC, 145
ERROR_REGRESS	dSTRmat, 148
messages.h, 239	ddenmat, 148
ERROR_SOLVER_EXIT	dvector, 148
messages.h, 239	FASP GSRB, 145
ERROR_SOLVER_MAXIT	FASP_USE_ILU, 145
messages.h, 239	GE, 145
ERROR_SOLVER_MISC	GT, 145
messages.h, 239	grid2d, 148
ERROR SOLVER STAG	iCOOmat, 148
messages.h, 240	iCSRmat, 149
ERROR_SOLVER_TYPE	IMAP, 149
messages.h, 240	INT, 146
ERROR WRONG FILE	ISNAN, 146
messages.h, 240	ISTART, 146
edges	idenmat, 149
•	,
grid2d, 33	ivector, 149
ediri	LE, 146
grid2d, 33	LONG, 146
efather	LS, 146
grid2d, 33	LinkList, 149
eigen.c, 139	ListElement, 149
fasp_dcsr_eig, 139	MAX, 146
endian_convert_int	MAX_AMG_LVL, 146
convert.c, 136	MAX_REFINE_LVL, 147
endian_convert_real	MAX_RESTART, 147
convert.c, 136	MAX_STAG, 147
	MAXIMAP, 149
FALSE	MIN, 147
messages.h, 240	N2C, 147
FASP_GET_START_END	NEDMALLOC, 147
threads.c, 410	nx_rb, 149
FASP_GSRB	ny_rb, 150
fasp.h, 145	nz_rb, 150
FASP_USE_ILU	OPENMP_HOLDS, 147
fasp.h, 145	pcgrid2d, 149
FGPT	pgrid2d, 149
messages.h, 240	REAL, 147
FPFIRST	SHORT, 147
messages.h, 240	SMALLREAL, 148
factor.f, 140	STAG_RATIO, 148
famg.c, 140	total_alloc_count, 150
fasp_solver_famg, 141	total_alloc_mem, 150
fasp.h, 141	fasp_BinarySearch
FASP_HEADER, 144	ordering.c, 257
ABS, 144	fasp_amg_amli_coef
BIGREAL, 144	amlirecur.c, 75
C2N, 144	fasp_amg_coarsening_cr
CHMEM_MODE, 145	coarsening_cr.c, 132
dCOOmat, 148	fasp_amg_coarsening_rs
dCSRLmat, 148	coarsening_rs.c, 134
dCSRmat, 148	fasp_amg_data_bsr_create
DEBUG_MODE, 145	init.c, 171

fasp_amg_data_bsr_free	fasp_aux_givens
init.c, 171	givens.c, 158
fasp_amg_data_create	fasp_aux_iQuickSort
init.c, 172	ordering.c, 254
fasp_amg_data_free	fasp_aux_iQuickSortIndex
init.c, 172	ordering.c, 254
fasp_amg_interp	fasp_aux_merge
interpolation.c, 180	ordering.c, 255
fasp_amg_interp1	fasp_aux_msort
interpolation.c, 181	ordering.c, 255
fasp_amg_interp_em	fasp_aux_unique
interpolation_em.c, 182	ordering.c, 255
fasp_amg_interp_trunc	fasp_blas_array_ax
interpolation.c, 181	blas_array.c, 82
fasp_amg_setup_cr	fasp_blas_array_axpby
amg_setup_cr.c, 67	blas_array.c, 82
fasp_amg_setup_rs	fasp_blas_array_axpy
amg_setup_rs.c, 68	blas_array.c, 83
fasp_amg_setup_rs_omp	fasp_blas_array_axpy_nc2
amg_setup_rs.c, 68	blas_smat.c, 104
fasp_amg_setup_sa	fasp_blas_array_axpy_nc3
amg_setup_sa.c, 69	blas_smat.c, 104
fasp_amg_setup_ua	fasp_blas_array_axpy_nc5
amg_setup_ua.c, 71	blas_smat.c, 105
fasp_amg_setup_ua_bsr	fasp_blas_array_axpy_nc7
amg_setup_ua.c, 71	blas_smat.c, 105
fasp_amg_solve	fasp_blas_array_axpyz
amg_solve.c, 72	blas_array.c, 83
fasp_amg_solve_amli	fasp_blas_array_axpyz_nc2
amg_solve.c, 72	blas_smat.c, 105
fasp_amg_solve_nl_amli	fasp_blas_array_axpyz_nc3
amg_solve.c, 73	blas_smat.c, 106
fasp_array_cp	fasp_blas_array_axpyz_nc5
array.c, 78	blas_smat.c, 106
fasp_array_cp_nc3	fasp_blas_array_axpyz_nc7
array.c, 78	blas_smat.c, 107
fasp_array_cp_nc5	fasp_blas_array_dotprod
array.c, 79	blas_array.c, 84
fasp_array_cp_nc7	fasp_blas_array_norm1
array.c, 79	blas_array.c, 84
fasp_array_null	fasp_blas_array_norm2
array.c, 79	blas_array.c, 85
fasp_array_set	fasp_blas_array_norminf
array.c, 80	blas_array.c, 85
fasp_aux_bbyteToldouble	fasp_blas_bdbsr_aAxpy
convert.c, 136	blas_bcsr.c, 87
fasp_aux_change_endian4	fasp_blas_bdbsr_mxv
convert.c, 138	blas_bcsr.c, 88
fasp_aux_change_endian8	fasp_blas_bdcsr_aAxpy
convert.c, 138	blas_bcsr.c, 88
fasp_aux_dQuickSort	fasp_blas_bdcsr_mxv
ordering.c, 253	blas_bcsr.c, 88
fasp_aux_dQuickSortIndex	fasp_blas_dbsr_aAxpby
ordering.c, 253	blas_bsr.c, 90
	-

fasp_blas_dbsr_aAxpy	fasp_blas_dvec_relerr
blas_bsr.c, 91	blas_vec.c, 126
fasp_blas_dbsr_mxv	fasp_blas_smat_aAxpby
blas_bsr.c, 91	blas_smat.c, 107
fasp_blas_dbsr_rap	fasp_blas_smat_inv
blas_bsr.c, 93	smat.c, 325
fasp_blas_dbsr_rap1	fasp_blas_smat_inv_nc2
blas_bsr.c, 93	smat.c, 325
fasp_blas_dcsr_aAxpy	fasp_blas_smat_inv_nc3
blas_csr.c, 95	smat.c, 325
fasp_blas_dcsr_aAxpy_agg	fasp_blas_smat_inv_nc4
blas_csr.c, 95	smat.c, 326
fasp_blas_dcsr_add	fasp_blas_smat_inv_nc5
blas_csr.c, 96	smat.c, 326
fasp_blas_dcsr_axm	fasp_blas_smat_inv_nc7
blas_csr.c, 96	smat.c, 326
fasp_blas_dcsr_mxm	fasp_blas_smat_mul
blas_csr.c, 97	blas_smat.c, 108
fasp_blas_dcsr_mxv	fasp_blas_smat_mul_nc2
blas_csr.c, 97	blas_smat.c, 108
fasp_blas_dcsr_mxv_agg	fasp_blas_smat_mul_nc3
blas_csr.c, 98	blas_smat.c, 109
fasp_blas_dcsr_ptap	fasp_blas_smat_mul_nc5
blas_csr.c, 98	blas_smat.c, 109
fasp_blas_dcsr_rap	fasp_blas_smat_mul_nc7
blas_csr.c, 99	blas_smat.c, 109
fasp_blas_dcsr_rap2	fasp_blas_smat_mxv
rap.c, 321	blas_smat.c, 110
fasp_blas_dcsr_rap4	fasp_blas_smat_mxv_nc2
blas_csr.c, 99	blas_smat.c, 110
fasp_blas_dcsr_rap_agg	fasp_blas_smat_mxv_nc3
blas_csr.c, 100	blas_smat.c, 110
fasp_blas_dcsr_rap_agg1	fasp_blas_smat_mxv_nc5
blas_csr.c, 100	blas_smat.c, 112
fasp_blas_dcsr_vmv	fasp_blas_smat_mxv_nc7
blas_csr.c, 101	blas_smat.c, 112
fasp_blas_dcsrl_mxv	fasp_blas_smat_ymAx
blas_csrl.c, 102	blas_smat.c, 112
fasp_blas_dstr_aAxpy	fasp_blas_smat_ymAx_nc2
blas_str.c, 122	blas_smat.c, 114
fasp_blas_dstr_mxv	fasp_blas_smat_ymAx_nc3
blas_str.c, 122	blas_smat.c, 114
fasp_blas_dvec_axpy	fasp_blas_smat_ymAx_nc5
blas_vec.c, 124	blas_smat.c, 115
fasp_blas_dvec_axpyz	fasp_blas_smat_ymAx_nc7
blas_vec.c, 124	blas_smat.c, 115
fasp_blas_dvec_dotprod	fasp_blas_smat_ymAx_ns
blas_vec.c, 124	blas_smat.c, 116
fasp_blas_dvec_norm1	fasp_blas_smat_ymAx_ns2
blas_vec.c, 125	blas_smat.c, 116
fasp_blas_dvec_norm2	fasp_blas_smat_ymAx_ns3
blas_vec.c, 125	blas_smat.c, 117
fasp_blas_dvec_norminf	fasp_blas_smat_ymAx_ns5
blas_vec.c, 126	blas_smat.c, 117

fasp_blas_smat_ymAx_ns7	sparse_block.c, 356
blas_smat.c, 118	fasp_dbsr_getblk_dcsr
fasp_blas_smat_ypAx	sparse_block.c, 356
blas_smat.c, 118	fasp_dbsr_getdiag
fasp_blas_smat_ypAx_nc2	sparse_bsr.c, 362
blas_smat.c, 119	fasp_dbsr_getdiaginv
fasp_blas_smat_ypAx_nc3	sparse_bsr.c, 363
blas_smat.c, 119	fasp_dbsr_null
fasp_blas_smat_ypAx_nc5	sparse_bsr.c, 363
blas_smat.c, 119	fasp_dbsr_print
fasp_blas_smat_ypAx_nc7	io.c, 185
blas_smat.c, 121	fasp_dbsr_read
fasp_block.h, 150	io.c, 185
block_BSR, 151	fasp_dbsr_trans
block_Reservoir, 152	sparse_bsr.c, 364
block dCSRmat, 151	fasp_dbsr_write
block_dvector, 151	io.c, 186
block_iCSRmat, 152	fasp_dcoo1_read
block_ivector, 152	io.c, 186
dBSRmat, 152	fasp_dcoo_alloc
precond_block_reservoir_data, 152	sparse coo.c, 365
fasp check dCSRmat	fasp_dcoo_create
checkmat.c, 128	sparse coo.c, 365
fasp_check_diagdom	fasp_dcoo_free
checkmat.c, 128	sparse coo.c, 365
fasp_check_diagpos	fasp_dcoo_print
checkmat.c, 128	io.c, 187
	fasp_dcoo_read
fasp_check_diagzero	
checkmat.c, 130	io.c, 187
fasp_check_iCSRmat	fasp_dcoo_shift
-ll 1 100	
checkmat.c, 130	sparse_coo.c, 366
fasp_check_symm	fasp_dcoo_write
fasp_check_symm checkmat.c, 130	fasp_dcoo_write io.c, 188
fasp_check_symm     checkmat.c, 130 fasp_chkerr	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc
fasp_check_symm checkmat.c, 130 fasp_chkerr message.c, 231	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369 fasp_dcsr_create
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369 fasp_dcsr_create sparse_csr.c, 369
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369 fasp_dcsr_create sparse_csr.c, 369 fasp_dcsr_diagpref
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369 fasp_dcsr_create sparse_csr.c, 369 fasp_dcsr_diagpref sparse_csr.c, 370
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369 fasp_dcsr_create sparse_csr.c, 369 fasp_dcsr_diagpref sparse_csr.c, 370 fasp_dcsr_eig
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369 fasp_dcsr_create sparse_csr.c, 369 fasp_dcsr_diagpref sparse_csr.c, 370 fasp_dcsr_eig eigen.c, 139
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369 fasp_dcsr_create sparse_csr.c, 369 fasp_dcsr_diagpref sparse_csr.c, 370 fasp_dcsr_eig eigen.c, 139 fasp_dcsr_free
fasp_check_symm	fasp_dcoo_write io.c, 188 fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369 fasp_dcsr_create sparse_csr.c, 369 fasp_dcsr_diagpref sparse_csr.c, 370 fasp_dcsr_eig eigen.c, 139 fasp_dcsr_free sparse_csr.c, 370
fasp_check_symm	fasp_dcoo_write io.c, 188  fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369 fasp_dcsr_create sparse_csr.c, 369 fasp_dcsr_diagpref sparse_csr.c, 370 fasp_dcsr_eig eigen.c, 139 fasp_dcsr_free sparse_csr.c, 370 fasp_dcsr_free sparse_csr.c, 370 fasp_dcsr_getblk
fasp_check_symm	fasp_dcoo_write io.c, 188  fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369 fasp_dcsr_create sparse_csr.c, 369 fasp_dcsr_diagpref sparse_csr.c, 370 fasp_dcsr_eig eigen.c, 139 fasp_dcsr_free sparse_csr.c, 370 fasp_dcsr_getblk sparse_block.c, 357
fasp_check_symm	fasp_dcoo_write io.c, 188  fasp_dcsr_alloc sparse_csr.c, 368 fasp_dcsr_compress sparse_csr.c, 368 fasp_dcsr_compress_inplace sparse_csr.c, 368 fasp_dcsr_cp sparse_csr.c, 369 fasp_dcsr_create sparse_csr.c, 369 fasp_dcsr_diagpref sparse_csr.c, 370 fasp_dcsr_eig eigen.c, 139 fasp_dcsr_free sparse_csr.c, 370 fasp_dcsr_getblk sparse_block.c, 357 fasp_dcsr_getcol

sparse_csr.c, 371	io.c, 193
fasp_dcsr_multicoloring	fasp_dstr_read
sparse_csr.c, 371	io.c, 194
fasp_dcsr_null	fasp_dstr_write
sparse_csr.c, 373	io.c, 194
fasp_dcsr_perm	fasp_dvec_alloc
sparse_csr.c, 373	vec.c, 413
fasp_dcsr_plot	fasp_dvec_cp
graphics.c, 165	vec.c, 413
fasp_dcsr_print	fasp_dvec_create
io.c, 188	vec.c, 413
fasp_dcsr_read	fasp_dvec_free
io.c, 188	vec.c, 414
fasp_dcsr_regdiag	fasp_dvec_isnan
sparse_csr.c, 374	vec.c, 414
fasp_dcsr_shift	fasp_dvec_maxdiff
sparse_csr.c, 374	vec.c, 414
fasp_dcsr_sort	fasp_dvec_null
sparse_csr.c, 374	vec.c, 415
fasp_dcsr_symdiagscale	fasp_dvec_print
sparse_csr.c, 376	io.c, 195
fasp_dcsr_sympat	fasp_dvec_rand
sparse_csr.c, 376	vec.c, 415
fasp_dcsr_trans	fasp_dvec_read
sparse_csr.c, 376	io.c, 195
fasp_dcsrl_create	fasp_dvec_set
sparse_csrl.c, 380	vec.c, 416
fasp dcsrl free	fasp dvec symdiagscale
fasp_dcsrl_free sparse_csrl.c. 381	fasp_dvec_symdiagscale vec.c. 416
sparse_csrl.c, 381	vec.c, 416
sparse_csrl.c, 381 fasp_dcsrvec1_read	vec.c, 416 fasp_dvec_write
sparse_csrl.c, 381 fasp_dcsrvec1_read io.c, 190	vec.c, 416 fasp_dvec_write io.c, 196
sparse_csrl.c, 381 fasp_dcsrvec1_read io.c, 190 fasp_dcsrvec1_write	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read
sparse_csrl.c, 381 fasp_dcsrvec1_read     io.c, 190 fasp_dcsrvec1_write     io.c, 190	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196
sparse_csrl.c, 381 fasp_dcsrvec1_read     io.c, 190 fasp_dcsrvec1_write     io.c, 190 fasp_dcsrvec2_read	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write
sparse_csrl.c, 381 fasp_dcsrvec1_read     io.c, 190 fasp_dcsrvec1_write     io.c, 190 fasp_dcsrvec2_read     io.c, 191	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196
sparse_csrl.c, 381 fasp_dcsrvec1_read     io.c, 190 fasp_dcsrvec1_write     io.c, 190 fasp_dcsrvec2_read     io.c, 191 fasp_dcsrvec2_write	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve
sparse_csrl.c, 381 fasp_dcsrvec1_read     io.c, 190 fasp_dcsrvec1_write     io.c, 190 fasp_dcsrvec2_read     io.c, 191 fasp_dcsrvec2_write     io.c, 192	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr formats.c, 154
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr formats.c, 154 fasp_format_dbsr_dcoo
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr formats.c, 154 fasp_format_dbsr_dcoo formats.c, 154
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr formats.c, 154 fasp_format_dbsr_dcoo formats.c, 154 fasp_format_dbsr_dcsr
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc     sparse_str.c, 382	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr formats.c, 154 fasp_format_dbsr_dcoo formats.c, 154 fasp_format_dbsr_dcsr format_dbsr_dcsr formats.c, 154
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc     sparse_str.c, 382  fasp_dstr_cp	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr formats.c, 154 fasp_format_dbsr_dcoo formats.c, 154 fasp_format_dbsr_dcsr format_dbsr_dcsr formats.c, 154 fasp_format_dbsr_dcsr formats.c, 154 fasp_format_dcoo_dcsr
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc     sparse_str.c, 382  fasp_dstr_cp     sparse_str.c, 382	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr formats.c, 154 fasp_format_dbsr_dcoo formats.c, 154 fasp_format_dbsr_dcsr format_c, 154 fasp_format_dbsr_dcsr formats.c, 154 fasp_format_dcsr_dcsr formats.c, 154 fasp_format_dcsr_dcsr formats.c, 155
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc     sparse_str.c, 382  fasp_dstr_cp     sparse_str.c, 382  fasp_dstr_create	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr formats.c, 154 fasp_format_dbsr_dcoo formats.c, 154 fasp_format_dbsr_dcsr format_dbsr_dcsr formats.c, 154 fasp_format_dcsr_dcsr formats.c, 154 fasp_format_dcsr_dcsr formats.c, 155 fasp_format_dcsr_dbsr
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc     sparse_str.c, 382  fasp_dstr_cp     sparse_str.c, 382  fasp_dstr_create     sparse_str.c, 383	vec.c, 416 fasp_dvec_write     io.c, 196 fasp_dvecind_read     io.c, 196 fasp_dvecind_write     io.c, 196 fasp_famg_solve     amg_solve.c, 73 fasp_format_bdcsr_dcsr     formats.c, 154 fasp_format_dbsr_dcoo     formats.c, 154 fasp_format_dbsr_dcsr     formats.c, 154 fasp_format_dbsr_dcsr     formats.c, 155 fasp_format_dcoo_dcsr     formats.c, 155 fasp_format_dcsr_dbsr     formats.c, 155
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc     sparse_str.c, 382  fasp_dstr_cp     sparse_str.c, 382  fasp_dstr_create     sparse_str.c, 383  fasp_dstr_diagscale	vec.c, 416 fasp_dvec_write     io.c, 196 fasp_dvecind_read     io.c, 196 fasp_dvecind_write     io.c, 196 fasp_famg_solve     amg_solve.c, 73 fasp_format_bdcsr_dcsr     formats.c, 154 fasp_format_dbsr_dcoo     formats.c, 154 fasp_format_dbsr_dcsr     format_dbsr_dcsr     formats.c, 154 fasp_format_dbsr_dcsr     formats.c, 155 fasp_format_dcsr_dbsr     formats.c, 155 fasp_format_dcsr_dcsoo
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc     sparse_str.c, 382  fasp_dstr_cp     sparse_str.c, 382  fasp_dstr_create     sparse_str.c, 383  fasp_dstr_diagscale     blas_str.c, 122	vec.c, 416 fasp_dvec_write
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc     sparse_str.c, 382  fasp_dstr_cp     sparse_str.c, 382  fasp_dstr_create     sparse_str.c, 383  fasp_dstr_diagscale     blas_str.c, 122  fasp_dstr_free	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr formats.c, 154 fasp_format_dbsr_dcoo formats.c, 154 fasp_format_dbsr_dcsr format_c, 154 fasp_format_dcsr_dcsr formats.c, 155 fasp_format_dcoo_dcsr formats.c, 155 fasp_format_dcsr_dbsr formats.c, 155 fasp_format_dcsr_dcoo formats.c, 156 fasp_format_dcsr_dcoo
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc     sparse_str.c, 382  fasp_dstr_cp     sparse_str.c, 382  fasp_dstr_create     sparse_str.c, 383  fasp_dstr_diagscale     blas_str.c, 122  fasp_dstr_free     sparse_str.c, 383	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr formats.c, 154 fasp_format_dbsr_dcoo formats.c, 154 fasp_format_dbsr_dcsr formats.c, 154 fasp_format_dcsr_dcsr formats.c, 155 fasp_format_dcsr_dbsr formats.c, 155 fasp_format_dcsr_dbsr formats.c, 155 fasp_format_dcsr_dcsr formats.c, 156 fasp_format_dcsr_dcoo formats.c, 156 fasp_format_dcsr_dcsr formats.c, 156
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc     sparse_str.c, 382  fasp_dstr_cp     sparse_str.c, 382  fasp_dstr_create     sparse_str.c, 383  fasp_dstr_diagscale     blas_str.c, 122  fasp_dstr_free     sparse_str.c, 383  fasp_dstr_free     sparse_str.c, 383  fasp_dstr_free     sparse_str.c, 383  fasp_dstr_free	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr formats.c, 154 fasp_format_dbsr_dcoo formats.c, 154 fasp_format_dbsr_dcsr formats.c, 154 fasp_format_dcsr_dcsr formats.c, 155 fasp_format_dcsr_dbsr formats.c, 155 fasp_format_dcsr_dbsr formats.c, 155 fasp_format_dcsr_dcsr formats.c, 156 fasp_format_dcsr_dcsr formats.c, 156 fasp_format_dcsr_dbsr
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec2_write     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc     sparse_str.c, 382  fasp_dstr_cp     sparse_str.c, 382  fasp_dstr_create     sparse_str.c, 383  fasp_dstr_diagscale     blas_str.c, 122  fasp_dstr_free     sparse_str.c, 383  fasp_dstr_free     sparse_str.c, 383  fasp_dstr_free     sparse_str.c, 383  fasp_dstr_null     sparse_str.c, 383	vec.c, 416 fasp_dvec_write     io.c, 196 fasp_dvecind_read     io.c, 196 fasp_dvecind_write     io.c, 196 fasp_famg_solve     amg_solve.c, 73 fasp_format_bdcsr_dcsr     formats.c, 154 fasp_format_dbsr_dcoo     formats.c, 154 fasp_format_dbsr_dcsr     formats.c, 154 fasp_format_dcsr_dcsr     formats.c, 155 fasp_format_dcsr_dbsr     formats.c, 155 fasp_format_dcsr_dcsr     formats.c, 155 fasp_format_dcsr_dcsr     formats.c, 156 fasp_format_dcsr_dcsr     formats.c, 156 fasp_format_dstr_dbsr     formats.c, 156 fasp_format_dstr_dbsr     formats.c, 157
sparse_csrl.c, 381  fasp_dcsrvec1_read     io.c, 190  fasp_dcsrvec1_write     io.c, 190  fasp_dcsrvec2_read     io.c, 191  fasp_dcsrvec2_write     io.c, 192  fasp_dmtx_read     io.c, 192  fasp_dmtxsym_read     io.c, 193  fasp_dstr_alloc     sparse_str.c, 382  fasp_dstr_cp     sparse_str.c, 382  fasp_dstr_create     sparse_str.c, 383  fasp_dstr_diagscale     blas_str.c, 122  fasp_dstr_free     sparse_str.c, 383  fasp_dstr_free     sparse_str.c, 383  fasp_dstr_free     sparse_str.c, 383  fasp_dstr_free	vec.c, 416 fasp_dvec_write io.c, 196 fasp_dvecind_read io.c, 196 fasp_dvecind_write io.c, 196 fasp_famg_solve amg_solve.c, 73 fasp_format_bdcsr_dcsr formats.c, 154 fasp_format_dbsr_dcoo formats.c, 154 fasp_format_dbsr_dcsr formats.c, 154 fasp_format_dcsr_dcsr formats.c, 155 fasp_format_dcsr_dbsr formats.c, 155 fasp_format_dcsr_dbsr formats.c, 155 fasp_format_dcsr_dcsr formats.c, 156 fasp_format_dcsr_dcsr formats.c, 156 fasp_format_dcsr_dbsr

formate a 157	voo o 410
formats.c, 157	vec.c, 419
fasp_fwrapper_amg_	fasp_ivec_write
wrapper.c, 420	io.c, 199
fasp_fwrapper_krylov_amg_	fasp_ivecind_read
wrapper.c, 420	io.c, 199
fasp_gauss2d	fasp_matrix_read
quadrature.c, 320	io.c, 200
fasp_generate_diaginv_block	fasp_matrix_read_bin
smoother_str.c, 348	io.c, 200
fasp_gettime	fasp_matrix_write
timing.c, 411	io.c, 201
fasp_grid2d_plot	fasp_mem_calloc
graphics.c, 165	memory.c, 226
fasp_iarray_cp	fasp_mem_check
array.c, 80	memory.c, 226
fasp_iarray_set	fasp_mem_dcsr_check
array.c, 81	memory.c, 228
fasp_icsr_cp	fasp_mem_free
sparse_csr.c, 378	memory.c, 228
fasp_icsr_create	fasp_mem_iludata_check
sparse_csr.c, 378	memory.c, 229
fasp_icsr_free	fasp_mem_realloc
sparse_csr.c, 379	memory.c, 229
fasp_icsr_null	fasp_mem_usage
sparse_csr.c, 379	memory.c, 229
fasp_icsr_trans	fasp_param_amg_init
sparse_csr.c, 379	parameters.c, 259
fasp_iden_free	fasp_param_amg_print
smat.c, 327	parameters.c, 260
fasp_ilu_data_alloc	fasp_param_amg_set
init.c, 173	parameters.c, 260
fasp_ilu_data_free	fasp_param_amg_to_prec
init.c, 173	parameters.c, 260
fasp_ilu_data_null	fasp_param_amg_to_prec_bsr
init.c, 173	parameters.c, 261
fasp_ilu_dbsr_setup	fasp_param_ilu_init
ilu_setup_bsr.c, 167	parameters.c, 261
fasp_ilu_dcsr_setup	fasp_param_ilu_print
ilu_setup_csr.c, 168	parameters.c, 261
fasp_ilu_dstr_setup0	fasp_param_ilu_set
ilu_setup_str.c, 169	parameters.c, 262
fasp_ilu_dstr_setup1	fasp_param_init
ilu_setup_str.c, 170	parameters.c, 262
fasp_ivec_alloc	fasp_param_input
vec.c, 417	input.c, 175
fasp ivec create	fasp_param_input_init
vec.c, 417	parameters.c, 263
	•
fasp_ivec_free	fasp_param_prec_to_amg
vec.c, 417	parameters.c, 263
fasp_ivec_print	fasp_param_prec_to_amg_bsr
io.c, 198	parameters.c, 263
fasp_ivec_read	fasp_param_schwarz_init
io.c, 198	parameters.c, 264
fasp_ivec_set	fasp_param_schwarz_print

parameters.c, 264	precond_str.c, 305
fasp_param_schwarz_set	fasp_precond_dstr_ilu0
parameters.c, 264	precond_str.c, 306
fasp_param_solver_init	fasp_precond_dstr_ilu0_backward precond str.c, 306
parameters.c, 265	• –
fasp_param_solver_print	fasp_precond_dstr_ilu0_forward
parameters.c, 265	precond_str.c, 306 fasp_precond_dstr_ilu1
fasp_param_solver_set parameters.c, 265	precond_str.c, 308
fasp_poisson_fgmg_1D	fasp_precond_dstr_ilu1_backward
gmg_poisson.c, 159	precond_str.c, 308
fasp_poisson_fgmg_2D	fasp_precond_dstr_ilu1_forward
gmg_poisson.c, 160	precond_str.c, 308
fasp_poisson_fgmg_3D	fasp_precond_famg
gmg_poisson.c, 160	precond_csr.c, 300
fasp_poisson_gmg_1D	fasp_precond_free
gmg_poisson.c, 161	precond_csr.c, 301
fasp_poisson_gmg_2D	fasp_precond_ilu
gmg_poisson.c, 161	precond_csr.c, 301
fasp_poisson_gmg_3D	fasp_precond_ilu_backward
gmg poisson.c, 162	precond_csr.c, 301
fasp_poisson_pcg_gmg_1D	fasp_precond_ilu_forward
gmg_poisson.c, 162	precond_csr.c, 302
fasp_poisson_pcg_gmg_2D	fasp_precond_nl_amli
gmg_poisson.c, 163	precond_csr.c, 302
fasp_poisson_pcg_gmg_3D	fasp_precond_null
gmg_poisson.c, 163	init.c, 174
fasp_precond_amg	fasp_precond_schwarz
precond_csr.c, 299	precond_csr.c, 302
fasp_precond_amli	fasp_precond_setup
precond_csr.c, 299	precond_csr.c, 304
fasp_precond_data_null	fasp_quad2d
parameters.c, 266	quadrature.c, 320
fasp_precond_dbsr_amg	fasp_schwarz_data_free
precond_bsr.c, 292	init.c, 174
fasp_precond_dbsr_diag	fasp_schwarz_setup
precond_bsr.c, 292	schwarz_setup.c, 323
fasp_precond_dbsr_diag_nc2	fasp_set_GS_threads
precond_bsr.c, 292	itsolver_bsr.c, 206
fasp_precond_dbsr_diag_nc3	fasp_smat_identity
precond_bsr.c, 294	smat.c, 327
fasp_precond_dbsr_diag_nc5	fasp_smat_identity_nc2
precond_bsr.c, 294	smat.c, 327
fasp_precond_dbsr_diag_nc7	fasp_smat_identity_nc3
precond_bsr.c, 296	smat.c, 329
fasp_precond_dbsr_ilu	fasp_smat_identity_nc5
precond_bsr.c, 296	smat.c, 329
fasp_precond_dbsr_nl_amli	fasp_smat_identity_nc7
precond_bsr.c, 298	smat.c, 329
fasp_precond_diag	fasp_smat_lu_decomp
precond_csr.c, 300	lu.c, 224
fasp_precond_dstr_blockgs	fasp_smat_lu_solve
precond_str.c, 305	lu.c, 225
fasp_precond_dstr_diag	fasp_smoother_dbsr_gs

smoother_bsr.c, 331	smoother_str.c, 348
fasp_smoother_dbsr_gs1	fasp_smoother_dstr_gs1
smoother_bsr.c, 331	smoother_str.c, 349
fasp_smoother_dbsr_gs_ascend	fasp_smoother_dstr_gs_ascend
smoother_bsr.c, 332	smoother_str.c, 349
fasp_smoother_dbsr_gs_descend	fasp_smoother_dstr_gs_cf
smoother_bsr.c, 332	smoother_str.c, 350
fasp_smoother_dbsr_gs_order1	fasp_smoother_dstr_gs_descend
smoother bsr.c, 333	smoother_str.c, 350
fasp_smoother_dbsr_gs_order2	fasp_smoother_dstr_gs_order
smoother bsr.c, 333	smoother_str.c, 351
fasp_smoother_dbsr_ilu	fasp smoother dstr jacobi
smoother_bsr.c, 334	smoother_str.c, 351
fasp_smoother_dbsr_jacobi	fasp_smoother_dstr_jacobi1
smoother_bsr.c, 334	smoother_str.c, 352
fasp_smoother_dbsr_jacobi1	fasp_smoother_dstr_schwarz
smoother_bsr.c, 334	smoother_str.c, 352
fasp_smoother_dbsr_jacobi_setup	fasp_smoother_dstr_sor
smoother_bsr.c, 336	smoother_str.c, 352
fasp_smoother_dbsr_sor	fasp smoother dstr sor1
smoother_bsr.c, 336	smoother str.c, 353
fasp_smoother_dbsr_sor1	fasp_smoother_dstr_sor_ascend
smoother_bsr.c, 337	smoother_str.c, 353
fasp smoother dbsr sor ascend	fasp_smoother_dstr_sor_cf
smoother_bsr.c, 337	smoother_str.c, 354
fasp_smoother_dbsr_sor_descend	fasp_smoother_dstr_sor_descend
smoother_bsr.c, 338	smoother_str.c, 354
fasp_smoother_dbsr_sor_order	fasp_smoother_dstr_sor_order
smoother_bsr.c, 338	smoother_str.c, 355
fasp_smoother_dcsr_L1diag	fasp_solver_amg
smoother_csr.c, 342	amg.c, 65
fasp_smoother_dcsr_gs	fasp_solver_amli
smoother_csr.c, 340	
	amlirecur.c, 76
fasp_smoother_dcsr_gs_cf	fasp_solver_bdcsr_itsolver
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340	fasp_solver_bdcsr_itsolver itsolver_bcsr.c, 204
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340 fasp_smoother_dcsr_gscr	fasp_solver_bdcsr_itsolver itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340 fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345	fasp_solver_bdcsr_itsolver itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov itsolver_bcsr.c, 205
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340 fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345 fasp_smoother_dcsr_ilu	fasp_solver_bdcsr_itsolver itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340 fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345 fasp_smoother_dcsr_ilu smoother_csr.c, 341	fasp_solver_bdcsr_itsolver itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs pbcgs.c, 268
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340 fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345 fasp_smoother_dcsr_ilu smoother_csr.c, 341 fasp_smoother_dcsr_jacobi	fasp_solver_bdcsr_itsolver itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs pbcgs.c, 268 fasp_solver_bdcsr_pcg
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340 fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345 fasp_smoother_dcsr_ilu smoother_csr.c, 341 fasp_smoother_dcsr_jacobi smoother_csr.c, 341	fasp_solver_bdcsr_itsolver itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs pbcgs.c, 268 fasp_solver_bdcsr_pcg pcg.c, 274
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340 fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345 fasp_smoother_dcsr_ilu smoother_csr.c, 341 fasp_smoother_dcsr_jacobi smoother_csr.c, 341 fasp_smoother_dcsr_kaczmarz	fasp_solver_bdcsr_itsolver itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs pbcgs.c, 268 fasp_solver_bdcsr_pcg pcg.c, 274 fasp_solver_bdcsr_pgmres
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340 fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345 fasp_smoother_dcsr_ilu smoother_csr.c, 341 fasp_smoother_dcsr_jacobi smoother_csr.c, 341 fasp_smoother_dcsr_kaczmarz smoother_csr.c, 342	fasp_solver_bdcsr_itsolver itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs pbcgs.c, 268 fasp_solver_bdcsr_pcg pcg.c, 274 fasp_solver_bdcsr_pgmres pgmres.c, 281
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340  fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345  fasp_smoother_dcsr_ilu smoother_csr.c, 341  fasp_smoother_dcsr_jacobi smoother_csr.c, 341  fasp_smoother_dcsr_kaczmarz smoother_csr.c, 342  fasp_smoother_dcsr_poly	fasp_solver_bdcsr_itsolver itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs pbcgs.c, 268 fasp_solver_bdcsr_pcg pcg.c, 274 fasp_solver_bdcsr_pgmres pgmres.c, 281 fasp_solver_bdcsr_pminres
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340 fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345 fasp_smoother_dcsr_ilu smoother_csr.c, 341 fasp_smoother_dcsr_jacobi smoother_csr.c, 341 fasp_smoother_dcsr_kaczmarz smoother_csr.c, 342 fasp_smoother_dcsr_poly smoother_csr_poly.c, 346	fasp_solver_bdcsr_itsolver     itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov     itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs     pbcgs.c, 268 fasp_solver_bdcsr_pcg     pcg.c, 274 fasp_solver_bdcsr_pgmres     pgmres.c, 281 fasp_solver_bdcsr_pminres     pminres.c, 287
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340 fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345 fasp_smoother_dcsr_ilu smoother_csr.c, 341 fasp_smoother_dcsr_jacobi smoother_csr.c, 341 fasp_smoother_dcsr_kaczmarz smoother_csr.c, 342 fasp_smoother_dcsr_poly smoother_csr_poly.c, 346 fasp_smoother_dcsr_poly_old	fasp_solver_bdcsr_itsolver     itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov     itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs     pbcgs.c, 268 fasp_solver_bdcsr_pcg     pcg.c, 274 fasp_solver_bdcsr_pgmres     pgmres.c, 281 fasp_solver_bdcsr_pminres     pminres.c, 287 fasp_solver_bdcsr_pvgmres
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340  fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345  fasp_smoother_dcsr_ilu smoother_csr.c, 341  fasp_smoother_dcsr_jacobi smoother_csr.c, 341  fasp_smoother_dcsr_kaczmarz smoother_dcsr_kaczmarz smoother_csr.c, 342  fasp_smoother_dcsr_poly smoother_csr_poly.c, 346  fasp_smoother_dcsr_poly_old smoother_csr_poly.c, 346	fasp_solver_bdcsr_itsolver     itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov     itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs     pbcgs.c, 268 fasp_solver_bdcsr_pcg     pcg.c, 274 fasp_solver_bdcsr_pgmres     pgmres.c, 281 fasp_solver_bdcsr_pminres     pminres.c, 287 fasp_solver_bdcsr_pvgmres     pvgmres.c, 315
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340  fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345  fasp_smoother_dcsr_ilu smoother_csr.c, 341  fasp_smoother_dcsr_jacobi smoother_csr.c, 341  fasp_smoother_dcsr_kaczmarz smoother_csr.c, 342  fasp_smoother_dcsr_poly smoother_csr_poly.c, 346  fasp_smoother_dcsr_poly_old smoother_csr_poly.c, 346  fasp_smoother_dcsr_sgs	fasp_solver_bdcsr_itsolver     itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov     itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs     pbcgs.c, 268 fasp_solver_bdcsr_pcg     pcg.c, 274 fasp_solver_bdcsr_pgmres     pgmres.c, 281 fasp_solver_bdcsr_pminres     pminres.c, 287 fasp_solver_bdcsr_pvgmres     pvgmres.c, 315 fasp_solver_bdcsr_spbcgs
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340  fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345  fasp_smoother_dcsr_ilu smoother_csr.c, 341  fasp_smoother_dcsr_jacobi smoother_csr.c, 341  fasp_smoother_dcsr_kaczmarz smoother_csr.c, 342  fasp_smoother_dcsr_poly smoother_csr_poly.c, 346  fasp_smoother_dcsr_poly_old smoother_csr_poly.c, 346  fasp_smoother_dcsr_sgs smoother_dcsr_sgs smoother_csr.c, 343	fasp_solver_bdcsr_itsolver     itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov     itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs     pbcgs.c, 268 fasp_solver_bdcsr_pcg     pcg.c, 274 fasp_solver_bdcsr_pgmres     pgmres.c, 281 fasp_solver_bdcsr_pminres     pminres.c, 287 fasp_solver_bdcsr_pvgmres     pvgmres.c, 315 fasp_solver_bdcsr_spbcgs     spbcgs.c, 393
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340  fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345  fasp_smoother_dcsr_ilu smoother_csr.c, 341  fasp_smoother_dcsr_jacobi smoother_csr.c, 341  fasp_smoother_dcsr_kaczmarz smoother_csr.c, 342  fasp_smoother_dcsr_poly smoother_csr_poly.c, 346  fasp_smoother_dcsr_poly_old smoother_csr_poly.c, 346  fasp_smoother_dcsr_sgs smoother_dcsr_sgs smoother_dcsr_sgs smoother_dcsr_sor	fasp_solver_bdcsr_itsolver     itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov     itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs     pbcgs.c, 268 fasp_solver_bdcsr_pcg     pcg.c, 274 fasp_solver_bdcsr_pgmres     pgmres.c, 281 fasp_solver_bdcsr_pminres     pminres.c, 287 fasp_solver_bdcsr_pvgmres     pvgmres.c, 315 fasp_solver_bdcsr_spbcgs     spbcgs.c, 393 fasp_solver_bdcsr_spcg
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340  fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345  fasp_smoother_dcsr_ilu smoother_csr.c, 341  fasp_smoother_dcsr_jacobi smoother_csr.c, 341  fasp_smoother_dcsr_kaczmarz smoother_csr.c, 342  fasp_smoother_dcsr_poly smoother_csr_poly.c, 346  fasp_smoother_dcsr_poly_old smoother_csr_poly.c, 346  fasp_smoother_dcsr_sgs smoother_dcsr_sgs smoother_csr.c, 343  fasp_smoother_dcsr_sor smoother_csr.c, 343	fasp_solver_bdcsr_itsolver     itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov     itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs     pbcgs.c, 268 fasp_solver_bdcsr_pcg     pcg.c, 274 fasp_solver_bdcsr_pgmres     pgmres.c, 281 fasp_solver_bdcsr_pminres     pminres.c, 287 fasp_solver_bdcsr_pvgmres     pvgmres.c, 315 fasp_solver_bdcsr_spbcgs     spbcgs.c, 393 fasp_solver_bdcsr_spcg     spcg.c, 398
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340  fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345  fasp_smoother_dcsr_ilu smoother_csr.c, 341  fasp_smoother_dcsr_jacobi smoother_csr.c, 341  fasp_smoother_dcsr_kaczmarz smoother_csr.c, 342  fasp_smoother_dcsr_poly smoother_csr_poly.c, 346  fasp_smoother_dcsr_poly_old smoother_csr_poly.c, 346  fasp_smoother_dcsr_sgs smoother_dcsr_sgs smoother_dcsr_sgs smoother_dcsr_sor smoother_dcsr_sor smoother_dcsr_sor	fasp_solver_bdcsr_itsolver     itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov     itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs     pbcgs.c, 268 fasp_solver_bdcsr_pcg     pcg.c, 274 fasp_solver_bdcsr_pgmres     pgmres.c, 281 fasp_solver_bdcsr_pminres     pminres.c, 287 fasp_solver_bdcsr_pvgmres     pvgmres.c, 315 fasp_solver_bdcsr_spbcgs     spbcgs.c, 393 fasp_solver_bdcsr_spcg     spcg.c, 398 fasp_solver_bdcsr_spgmres
fasp_smoother_dcsr_gs_cf smoother_csr.c, 340  fasp_smoother_dcsr_gscr smoother_csr_cr.c, 345  fasp_smoother_dcsr_ilu smoother_csr.c, 341  fasp_smoother_dcsr_jacobi smoother_csr.c, 341  fasp_smoother_dcsr_kaczmarz smoother_csr.c, 342  fasp_smoother_dcsr_poly smoother_csr_poly.c, 346  fasp_smoother_dcsr_poly_old smoother_csr_poly.c, 346  fasp_smoother_dcsr_sgs smoother_dcsr_sgs smoother_csr.c, 343  fasp_smoother_dcsr_sor smoother_csr.c, 343	fasp_solver_bdcsr_itsolver     itsolver_bcsr.c, 204 fasp_solver_bdcsr_krylov     itsolver_bcsr.c, 205 fasp_solver_bdcsr_pbcgs     pbcgs.c, 268 fasp_solver_bdcsr_pcg     pcg.c, 274 fasp_solver_bdcsr_pgmres     pgmres.c, 281 fasp_solver_bdcsr_pminres     pminres.c, 287 fasp_solver_bdcsr_pvgmres     pvgmres.c, 315 fasp_solver_bdcsr_spbcgs     spbcgs.c, 393 fasp_solver_bdcsr_spcg     spcg.c, 398

spminres.c, 405	pvgmres.c, 317
fasp_solver_bdcsr_spvgmres	fasp_solver_dcsr_spbcgs
spvgmres.c, 407	spbcgs.c, 394
fasp_solver_dbsr_itsolver	fasp_solver_dcsr_spcg
itsolver_bsr.c, 206	spcg.c, 399
fasp_solver_dbsr_krylov	fasp_solver_dcsr_spgmres
itsolver_bsr.c, 208	spgmres.c, 402
fasp_solver_dbsr_krylov_amg	fasp_solver_dcsr_spminres
itsolver_bsr.c, 208	spminres.c, 405
fasp_solver_dbsr_krylov_diag	fasp_solver_dcsr_spvgmres
itsolver_bsr.c, 209	spvgmres.c, 408
fasp_solver_dbsr_krylov_ilu	fasp_solver_dstr_itsolver
itsolver_bsr.c, 209	itsolver_str.c, 220
fasp_solver_dbsr_pbcgs	fasp_solver_dstr_krylov
pbcgs.c, 268	itsolver_str.c, 220
fasp_solver_dbsr_pgmres	fasp_solver_dstr_krylov_blockgs
pgmres.c, 281	itsolver_str.c, 221
fasp_solver_dbsr_pvfgmres	fasp_solver_dstr_krylov_diag
pvfgmres.c, 311	itsolver_str.c, 221
fasp_solver_dbsr_pvgmres	fasp_solver_dstr_krylov_ilu
pvgmres.c, 315	itsolver_str.c, 221
fasp_solver_dbsr_spbcgs	fasp_solver_dstr_pbcgs
spbcgs.c, 394	pbcgs.c, 270
fasp_solver_dbsr_spgmres	fasp_solver_dstr_pcg
spgmres.c, 401	pcg.c, 275
fasp_solver_dbsr_spvgmres	fasp_solver_dstr_pgmres
spvgmres.c, 408	pgmres.c, 284
fasp_solver_dcsr_itsolver	fasp_solver_dstr_pminres
itsolver_csr.c, 212	pminres.c, 288
fasp_solver_dcsr_krylov	fasp_solver_dstr_pvgmres
itsolver_csr.c, 213	pvgmres.c, 318
fasp_solver_dcsr_krylov_amg	fasp_solver_dstr_spbcgs
itsolver_csr.c, 213	spbcgs.c, 396
fasp_solver_dcsr_krylov_diag	fasp_solver_dstr_spcg
itsolver_csr.c, 214	spcg.c, 399
fasp_solver_dcsr_krylov_ilu	fasp_solver_dstr_spgmres
itsolver_csr.c, 214	spgmres.c, 402
fasp_solver_dcsr_krylov_ilu_M	fasp_solver_dstr_spminres
itsolver_csr.c, 215	spminres.c, 406
fasp_solver_dcsr_krylov_schwarz	fasp_solver_dstr_spvgmres spvgmres.c, 409
itsolver_csr.c, 215 fasp_solver_dcsr_pbcgs	
	face colver fama
	fasp_solver_famg
pbcgs.c, 269	famg.c, 141
pbcgs.c, 269 fasp_solver_dcsr_pcg	famg.c, 141 fasp_solver_fmgcycle
pbcgs.c, 269 fasp_solver_dcsr_pcg pcg.c, 274	famg.c, 141 fasp_solver_fmgcycle fmgcycle.c, 153
pbcgs.c, 269 fasp_solver_dcsr_pcg pcg.c, 274 fasp_solver_dcsr_pgcg	famg.c, 141 fasp_solver_fmgcycle fmgcycle.c, 153 fasp_solver_itsolver
pbcgs.c, 269 fasp_solver_dcsr_pcg pcg.c, 274 fasp_solver_dcsr_pgcg pgcg.c, 278	famg.c, 141 fasp_solver_fmgcycle fmgcycle.c, 153 fasp_solver_itsolver itsolver_mf.c, 217
pbcgs.c, 269 fasp_solver_dcsr_pcg     pcg.c, 274 fasp_solver_dcsr_pgcg     pgcg.c, 278 fasp_solver_dcsr_pgmres	famg.c, 141 fasp_solver_fmgcycle fmgcycle.c, 153 fasp_solver_itsolver itsolver_mf.c, 217 fasp_solver_itsolver_init
pbcgs.c, 269 fasp_solver_dcsr_pcg     pcg.c, 274 fasp_solver_dcsr_pgcg     pgcg.c, 278 fasp_solver_dcsr_pgmres     pgmres.c, 283	famg.c, 141 fasp_solver_fmgcycle fmgcycle.c, 153 fasp_solver_itsolver itsolver_mf.c, 217 fasp_solver_itsolver_init itsolver_mf.c, 218
pbcgs.c, 269 fasp_solver_dcsr_pcg     pcg.c, 274 fasp_solver_dcsr_pgcg     pgcg.c, 278 fasp_solver_dcsr_pgmres     pgmres.c, 283 fasp_solver_dcsr_pminres	famg.c, 141  fasp_solver_fmgcycle     fmgcycle.c, 153  fasp_solver_itsolver     itsolver_mf.c, 217  fasp_solver_itsolver_init     itsolver_mf.c, 218  fasp_solver_krylov
pbcgs.c, 269 fasp_solver_dcsr_pcg     pcg.c, 274 fasp_solver_dcsr_pgcg     pgcg.c, 278 fasp_solver_dcsr_pgmres     pgmres.c, 283 fasp_solver_dcsr_pminres     pminres.c, 288	famg.c, 141  fasp_solver_fmgcycle     fmgcycle.c, 153  fasp_solver_itsolver     itsolver_mf.c, 217  fasp_solver_itsolver_init     itsolver_mf.c, 218  fasp_solver_krylov     itsolver_mf.c, 218
pbcgs.c, 269  fasp_solver_dcsr_pcg     pcg.c, 274  fasp_solver_dcsr_pgcg     pgcg.c, 278  fasp_solver_dcsr_pgmres     pgmres.c, 283  fasp_solver_dcsr_pminres     pminres.c, 288  fasp_solver_dcsr_pvfgmres	famg.c, 141  fasp_solver_fmgcycle     fmgcycle.c, 153  fasp_solver_itsolver     itsolver_mf.c, 217  fasp_solver_itsolver_init     itsolver_mf.c, 218  fasp_solver_krylov     itsolver_mf.c, 218  fasp_solver_mgcycle
pbcgs.c, 269 fasp_solver_dcsr_pcg     pcg.c, 274 fasp_solver_dcsr_pgcg     pgcg.c, 278 fasp_solver_dcsr_pgmres     pgmres.c, 283 fasp_solver_dcsr_pminres     pminres.c, 288	famg.c, 141  fasp_solver_fmgcycle     fmgcycle.c, 153  fasp_solver_itsolver     itsolver_mf.c, 217  fasp_solver_itsolver_init     itsolver_mf.c, 218  fasp_solver_krylov     itsolver_mf.c, 218

mgcycle.c, 251	sparse_util.c, 391
fasp_solver_mgrecur	fasp_vector_read
mgrecur.c, 252	io.c, 201
fasp_solver_mumps	fasp_vector_write
interface_mumps.c, 176	io.c, 203
fasp_solver_mumps_steps	fasp_wrapper_dbsr_krylov_amg
interface_mumps.c, 176	wrapper.c, 421
fasp_solver_nl_amli	fasp_wrapper_dcoo_dbsr_krylov_amg
amlirecur.c, 76	wrapper.c, 421
fasp_solver_nl_amli_bsr	fmgcycle.c, 152
amlirecur.c, 77	fasp_solver_fmgcycle, 153
fasp_solver_pbcgs	formats.c, 153
pbcgs_mf.c, 272	fasp_format_bdcsr_dcsr, 154
fasp_solver_pcg	fasp_format_dbsr_dcoo, 154
pcg_mf.c, 277	fasp_format_dbsr_dcsr, 154
fasp_solver_pgcg	fasp_format_dcoo_dcsr, 155
pgcg_mf.c, 279	fasp_format_dcsr_dbsr, 155
fasp_solver_pgmres	fasp_format_dcsr_dcoo, 156
pgmres_mf.c, 285	fasp_format_dcsrl_dcsr, 156
fasp_solver_pminres	fasp format dstr dbsr, 157
pminres_mf.c, 290	fasp_format_dstr_dcsr, 157
fasp_solver_pvfgmres	
pvfgmres_mf.c, 313	GE
fasp_solver_pvgmres	fasp.h, 145
pvgmres_mf.c, 319	GT
fasp_solver_superlu	fasp.h, 145
interface_superlu.c, 178	givens.c, 158
fasp_solver_umfpack	fasp_aux_givens, 158
interface_umfpack.c, 179	gmg_poisson.c, 159
fasp_sparse_MIS	fasp_poisson_fgmg_1D, 159
sparse_util.c, 387	fasp_poisson_fgmg_2D, 160
fasp_sparse_aat_	fasp_poisson_fgmg_3D, 160
sparse_util.c, 385	fasp_poisson_gmg_1D, 161
	fasp poisson gmg 2D, 161
fasp_sparse_abyb_	
sparse_util.c, 385	fasp_poisson_gmg_3D, 162
fasp_sparse_abybms_	fasp_poisson_pcg_gmg_1D, 162
sparse_util.c, 386	fasp_poisson_pcg_gmg_2D, 163
fasp_sparse_aplbms_	fasp_poisson_pcg_gmg_3D, 163
sparse_util.c, 386	gmg_util.inl, 164
fasp_sparse_aplusb_	graphics.c, 164
sparse_util.c, 387	fasp_dcsr_plot, 165
fasp_sparse_iit_	fasp_grid2d_plot, 165
sparse_util.c, 387	grid2d, 32
fasp_sparse_rapcmp_	e, 33
sparse_util.c, 388	edges, <mark>33</mark>
fasp_sparse_rapms_	ediri, 33
sparse_util.c, 388	efather, 33
fasp_sparse_wta_	fasp.h, 148
sparse_util.c, 389	p, <mark>33</mark>
fasp_sparse_wtams_	pdiri, 33
sparse_util.c, 389	pfather, 33
fasp_sparse_ytx_	s, 33
sparse_util.c, 391	t, 33
fasp_sparse_ytxbig_	tfather, 34

triangles, 34	fasp_amg_data_create, 172
vertices, 34	fasp_amg_data_free, 172
	fasp_ilu_data_alloc, 173
iCOOmat, 34	fasp_ilu_data_free, 173
fasp.h, 148	fasp_ilu_data_null, 173
iCSRmat, 35	fasp_precond_null, 174
fasp.h, 149	fasp_schwarz_data_free, 174
ILU_data, 36	input.c, 174
ILU_droptol	fasp_param_input, 175
input_param, 42	input_param, 37
ILU_lfil	AMG_ILU_levels, 39
input_param, 42	AMG_aggressive_level, 39
ILU_param, 37	AMG_aggressive_path, 39
ILU_permtol	AMG_amli_degree, 39
input_param, 42	AMG_coarse_dof, 39
ILU_relax	AMG_coarse_scaling, 39
input_param, 42	AMG_coarsening_type, 39
ILU_type	AMG_cycle_type, 39
input_param, 42	AMG_interpolation_type, 40
ILUk	AMG levels, 40
messages.h, 241	AMG_max_aggregation, 40
ILUt	AMG max row sum, 40
messages.h, 241	AMG_maxit, 40
ILUtp	AMG_nl_amli_krylov_type, 40
messages.h, 241	AMG_polynomial_degree, 40
IMAP	AMG_postsmooth_iter, 40
fasp.h, 149	AMG_presmooth_iter, 40
INT	AMG_relaxation, 41
fasp.h, 146	AMG schwarz levels, 41
INTERP DIR	AMG smooth filter, 41
messages.h, 241	AMG_smooth_order, 41
INTERP_ENG	AMG_smoother, 41
messages.h, 241	AMG_strong_coupled, 41
INTERP_STD	AMG_strong_threshold, 41
messages.h, 241	AMG_tentative_smooth, 41
ISNAN	AMG_tol, 41
fasp.h, 146	AMG_truncation_threshold, 42
ISPT	AMG type, 42
messages.h, 241	ILU droptol, 42
ISTART	ILU Ifil, 42
fasp.h, 146	ILU permtol, 42
idenmat, 36	ILU_relax, 42
fasp.h, 149	ILU type, 42
ilu.f. 166	itsolver maxit, 42
ilu setup bsr.c, 166	itsolver tol, 42
fasp_ilu_dbsr_setup, 167	output type, 43
ilu setup csr.c, 168	precond type, 43
fasp_ilu_dcsr_setup, 168	print level, 43
ilu_setup_str.c, 169	problem_num, 43
fasp_ilu_dstr_setup0, 169	restart, 43
fasp_ilu_dstr_setup1, 170	Schwarz maxlvl, 43
init.c, 170	Schwarz mmsize, 43
fasp_amg_data_bsr_create, 171	Schwarz_type, 43
fasp_amg_data_bsr_free, 171	solver_type, 43
	33.731,po, 10

stop_type, 44	itsolver bsr.c, 205
workdir, 44	fasp_set_GS_threads, 206
interface_mumps.c, 175	fasp solver dbsr itsolver, 206
fasp_solver_mumps, 176	fasp_solver_dbsr_krylov, 208
fasp solver mumps steps, 176	fasp_solver_dbsr_krylov_amg, 208
interface samg.c, 177	fasp_solver_dbsr_krylov_diag, 209
dCSRmat2SAMGInput, 177	fasp_solver_dbsr_krylov_ilu, 209
dvector2SAMGInput, 177	THDs AMG GS, 211
interface_superlu.c, 178	THDs_CPR_gGS, 211
fasp_solver_superlu, 178	THDs_CPR_IGS, 211
interface_umfpack.c, 179	itsolver csr.c, 211
fasp_solver_umfpack, 179	fasp_solver_dcsr_itsolver, 212
interpolation.c, 180	fasp_solver_dcsr_krylov, 213
fasp_amg_interp, 180	fasp_solver_dcsr_krylov_amg, 213
	fasp_solver_dcsr_krylov_diag, 214
fasp_amg_interp1, 181	fasp_solver_dcsr_krylov_ilu, 214
fasp_amg_interp_trunc, 181	fasp_solver_dcsr_krylov_ilu_M, 215
interpolation_em.c, 182 fasp amg interp em, 182	fasp_solver_dcsr_krylov_schwarz, 215
	itsolver_maxit
io.c, 183	input_param, 42
fasp_dbsr_print, 185	itsolver_mf.c, 216
fasp_dbsr_read, 185	fasp_solver_itsolver, 217
fasp_dbsr_write, 186	fasp_solver_itsolver_init, 218
fasp_dcoo1_read, 186	fasp_solver_krylov, 218
fasp_dcoo_print, 187	itsolver_param, 44
fasp_dcoo_read, 187	itsolver_type, 44
fasp_dcoo_write, 188	maxit, 44
fasp_dcsr_print, 188	precond_type, 45
fasp_dcsr_read, 188	print_level, 45
fasp_dcsrvec1_read, 190	restart, 45
fasp_dcsrvec1_write, 190	stop_type, 45
fasp_dcsrvec2_read, 191	tol, 45
fasp_dcsrvec2_write, 192	itsolver_str.c, 219
fasp_dmtx_read, 192	fasp solver dstr itsolver, 220
fasp_dmtxsym_read, 193	fasp_solver_dstr_itsolver, 220
fasp_dstr_print, 193	fasp_solver_dstr_krylov, 220 fasp_solver_dstr_krylov_blockgs, 221
fasp_dstr_read, 194	· · - ·
fasp_dstr_write, 194	fasp_solver_dstr_krylov_diag, 221
fasp_dvec_print, 195	fasp_solver_dstr_krylov_ilu, 221
fasp_dvec_read, 195	itsolver_tol
fasp_dvec_write, 196	input_param, 42
fasp_dvecind_read, 196	itsolver_type
fasp_dvecind_write, 196	itsolver_param, 44
fasp_ivec_print, 198	itsolver_util.inl, 222
fasp_ivec_read, 198	ivector, 45
fasp_ivec_write, 199	fasp.h, 149
fasp_ivecind_read, 199	JA
fasp_matrix_read, 200	dBSRmat, 27
fasp_matrix_read_bin, 200	
fasp_matrix_write, 201	LE
fasp_vector_read, 201	fasp.h, 146
fasp_vector_write, 203	LIST_HEAD
itsolver_bcsr.c, 204	linklist.inl, 223
fasp_solver_bdcsr_itsolver, 204	LIST_TAIL
fasp_solver_bdcsr_krylov, 205	linklist.inl, 223
· — — — · ·	

LONG	fasp_mem_free, 228
fasp.h, 146	fasp_mem_iludata_check, 229
LS	fasp_mem_realloc, 229
fasp.h, 146	fasp_mem_usage, 229
Link, 46	total_alloc_count, 230
LinkList	total_alloc_mem, 230
fasp.h, 149	message.c, 230
linked_list, 46	fasp_chkerr, 231
linklist.inl, 223	print_amgcomplexity, 231
LIST HEAD, 223	print_amgcomplexity_bsr, 231
LIST TAIL, 223	print cputime, 232
ListElement	print_itinfo, 232
fasp.h, 149	print_message, 233
lu.c, 224	messages.h, 233
fasp_smat_lu_decomp, 224	AMLI CYCLE, 236
fasp_smat_lu_solve, 225	ASCEND, 236
183P_3118t_lu_301ve, 223	CF_ORDER, 236
MAT BSR	CGPT, 236
messages.h, 242	CLASSIC AMG, 237
	<del>-</del> · · · ·
MAT_CSR	COARSE_AC, 237
messages.h, 242	COARSE_CR, 237
MAT_CSRL	COARSE_RS, 237
messages.h, 242	CPFIRST, 237
MAT_FREE	DESCEND, 237
messages.h, 242	ERROR_ALLOC_MEM, 237
MAT_STR	ERROR_AMG_COARSEING, 238
messages.h, 242	ERROR_DATA_ZERODIAG, 238
MAT_SymCSR	ERROR_DUMMY_VAR, 238
messages.h, 242	ERROR_INPUT_PAR, 238
MAT_bBSR	ERROR_MISC, 238
messages.h, 241	ERROR_NUM_BLOCKS, 238
MAT_bCSR	ERROR_OPEN_FILE, 239
messages.h, 242	ERROR_QUAD_DIM, 239
MAX	ERROR_QUAD_TYPE, 239
fasp.h, 146	ERROR_REGRESS, 239
MAX_AMG_LVL	ERROR_SOLVER_EXIT, 239
fasp.h, 146	ERROR_SOLVER_MAXIT, 239
MAX_REFINE_LVL	ERROR_SOLVER_MISC, 239
fasp.h, 147	ERROR_SOLVER_STAG, 240
MAX_RESTART	ERROR_SOLVER_TYPE, 240
fasp.h, 147	ERROR_WRONG_FILE, 240
MAX_STAG	FALSE, 240
fasp.h, 147	FGPT, 240
MAXIMAP	FPFIRST, 240
fasp.h, 149	ILUk, 241
MIN	ILUt, 241
fasp.h, 147	ILUtp, 241
maxit	INTERP_DIR, 241
itsolver_param, 44	INTERP_ENG, 241
precond_FASP_blkoil_data, 60	INTERP_STD, 241
memory.c, 225	ISPT, 241
fasp_mem_calloc, 226	MAT_BSR, 242
fasp_mem_check, 226	MAT_CSR, 242
fasp_mem_dcsr_check, 228	MAT_CSRL, 242
· <del></del>	_

MAT_FREE, 242	STOP_REL_PRECRES, 248
MAT_STR, 242	STOP_REL_RES, 249
MAT_SymCSR, 242	SUCCESS, 249
MAT bBSR, 241	TRUE, 249
MAT bCSR, 242	UA AMG, 249
NL AMLI CYCLE, 242	UNPT, 249
NO ORDER, 243	USERDEFINED, 249
OFF, 243	V CYCLE, 249
ON, 243	W CYCLE, 250
PREC AMG, 243	mg_util.inl, 250
PREC DIAG, 243	mgcycle.c, 250
PREC FMG, 243	fasp_solver_mgcycle, 250
<del>-</del> · · · ·	fasp_solver_mgcycle_bsr, 251
PREC_ILU, 243	mgl_data
PREC_NULL, 243	precond_FASP_blkoil_data, 60
PREC_SCHWARZ, 244	mgrecur.c, 251
PRINT_ALL, 244	fasp_solver_mgrecur, 252
PRINT_MIN, 244	· — — -
PRINT_MORE, 244	mxv_matfree, 47
PRINT_MOST, 244	N2C
PRINT_NONE, 244	fasp.h, 147
PRINT_SOME, 244	NEDMALLOC
RUN_FAIL, 244	fasp.h, 147
SA_AMG, 245	NL AMLI CYCLE
SMOOTHER_BLKOIL, 245	
SMOOTHER_CG, 245	messages.h, 242
SMOOTHER_GS, 245	NO_ORDER
SMOOTHER_GSOR, 245	messages.h, 243
SMOOTHER_JACOBI, 245	neigh
SMOOTHER_L1DIAG, 245	precond_FASP_blkoil_data, 60
SMOOTHER_POLY, 245	nx_rb
SMOOTHER_SGS, 246	fasp.h, 149
SMOOTHER_SGSOR, 246	ny_rb
SMOOTHER_SOR, 246	fasp.h, 150
SMOOTHER SSOR, 246	nz_rb
SOLVER AMG, 246	fasp.h, 150
SOLVER BiCGstab, 246	OFF
SOLVER CG, 246	messages.h, 243
SOLVER FMG, 246	ON
SOLVER GCG, 247	messages.h, 243
SOLVER GMRES, 247	OPENMP_HOLDS
SOLVER MUMPS, 247	fasp.h, 147
SOLVER MinRes, 247	order
SOLVER SBiCGstab, 247	
SOLVER SCG, 247	precond_block_reservoir_data, 51
SOLVER SGCG, 247	precond_FASP_blkoil_data, 60
SOLVER_SGMRES, 247	ordering.c, 252
SOLVER SMinRes, 247	fasp_BinarySearch, 257
<del>-</del>	fasp_aux_dQuickSort, 253
SOLVER_SUPERLU, 248	fasp_aux_dQuickSortIndex, 253
SOLVER_SVEMPES, 248	fasp_aux_iQuickSort, 254
SOLVER_SVGMRES, 248	fasp_aux_iQuickSortIndex, 254
SOLVER_UMFPACK, 248	fasp_aux_merge, 255
SOLVER_VFGMRES, 248	fasp_aux_msort, 255
SOLVER_VGMRES, 248	fasp_aux_unique, 255
STOP_MOD_REL_RES, 248	output_type

input_param, 43	fasp_solver_dcsr_pbcgs, 269
	fasp_solver_dstr_pbcgs, 270
p	pbcgs_mf.c, 270
grid2d, 33	fasp_solver_pbcgs, 272
PP	pcg.c, 272
precond_block_reservoir_data, 51	fasp_solver_bdcsr_pcg, 274
precond_FASP_blkoil_data, 61	fasp_solver_dcsr_pcg, 274
PREC_AMG	fasp_solver_dstr_pcg, 275
messages.h, 243 PREC DIAG	pcg_mf.c, 276
<del>-</del>	fasp_solver_pcg, 277
messages.h, 243 PREC FMG	pcgrid2d
_	fasp.h, 149 pdiri
messages.h, 243 PREC ILU	grid2d, 33
<del>_</del>	-
messages.h, 243 PREC NULL	perf_idx precond block reservoir data, 51
messages.h, 243	precond FASP blkoil data, 60
PREC SCHWARZ	perf_neigh
messages.h, 244	precond FASP blkoil data, 60
PRINT ALL	pfather
<del>-</del>	grid2d, 33
messages.h, 244 PRINT MIN	
messages.h, 244	pgcg.c, 278 fasp_solver_dcsr_pgcg, 278
PRINT MORE	pgcg_mf.c, 279
messages.h, 244	fasp_solver_pgcg, 279
PRINT MOST	pgmres.c, 280
messages.h, 244	fasp_solver_bdcsr_pgmres, 281
PRINT NONE	fasp_solver_dbsr_pgmres, 281
messages.h, 244	fasp_solver_dcsr_pgmres, 283
PRINT SOME	fasp_solver_dstr_pgmres, 284
messages.h, 244	pgmres_mf.c, 284
parameters.c, 257	fasp solver pgmres, 285
fasp_param_amg_init, 259	pgrid2d
fasp_param_amg_print, 260	fasp.h, 149
fasp_param_amg_set, 260	pivot
fasp_param_amg_to_prec, 260	precond_block_reservoir_data, 51
fasp_param_amg_to_prec_bsr, 261	precond_FASP_blkoil_data, 60
fasp param ilu init, 261	pivot S
fasp_param_ilu_print, 261	precond_FASP_blkoil_data, 61
fasp_param_ilu_set, 262	pivotS
fasp_param_init, 262	precond_block_reservoir_data, 51
fasp_param_input_init, 263	pminres.c, 286
fasp param prec to amg, 263	fasp solver bdcsr pminres, 287
fasp param prec to amg bsr, 263	fasp_solver_dcsr_pminres, 288
fasp_param_schwarz_init, 264	fasp_solver_dstr_pminres, 288
fasp param schwarz print, 264	pminres mf.c, 289
fasp param schwarz set, 264	fasp solver pminres, 290
fasp_param_solver_init, 265	precond, 47
fasp_param_solver_print, 265	precond_FASP_blkoil_data, 58
fasp_param_solver_set, 265	A, 59
fasp_precond_data_null, 266	diaginv, 59
pbcgs.c, 266	diaginv_S, 60
fasp_solver_bdcsr_pbcgs, 268	diaginv_noscale, 60
fasp_solver_dbsr_pbcgs, 268	maxit, 60
· ·	

mgl_data, 60	fasp_precond_free, 301
neigh, 60	fasp_precond_ilu, 301
order, 60	fasp_precond_ilu_backward, 301
PP, 61	fasp_precond_ilu_forward, 302
perf_idx, 60	fasp_precond_nl_amli, 302
perf_neigh, 60	fasp_precond_schwarz, 302
pivot, 60	fasp_precond_setup, 304
pivot_S, 61	precond_data, 52
r, 61	precond_data_bsr, 54
RR, 61	precond_data_str, 55
restart, 61	precond diagbsr, 57
SS, 61	precond_diagstr, 57
scaled, 61	precond_str.c, 304
tol, 61	fasp_precond_dstr_blockgs, 305
w, 62	fasp_precond_dstr_diag, 305
WW, 62	fasp_precond_dstr_ilu0, 306
precond block data, 48	fasp_precond_dstr_ilu0_backward, 306
A, 48	fasp_precond_dstr_ilu0_forward, 306
Aarray, 48	fasp_precond_dstr_ilu1, 308
Ablock, 48	fasp_precond_dstr_ilu1_backward, 308
	fasp_precond_dstr_ilu1_forward, 308
amgparam, 49 col_idx, 49	. — — — —
	precond_type
r, 49	input_param, 43
row_idx, 49	itsolver_param, 45
precond_block_reservoir_data, 49	print_amgcomplexity
diag, 51	message.c, 231
diaginv, 51	print_amgcomplexity_bsr
diaginvS, 51	message.c, 231
fasp_block.h, 152	print_cputime
order, 51	message.c, 232
PP, 51	print_itinfo
perf_idx, 51	message.c, 232
pivot, 51	print_level
pivotS, 51	input_param, 43
r, 52	itsolver_param, 45
RR, 52	print_message
SS, 52	message.c, 233
scaled, 52	problem_num
w, 52	input_param, 43
WW, 52	pvfgmres.c, 310
precond_bsr.c, 291	fasp_solver_dbsr_pvfgmres, 311
fasp_precond_dbsr_amg, 292	fasp_solver_dcsr_pvfgmres, 312
fasp_precond_dbsr_diag, 292	pvfgmres_mf.c, 313
fasp_precond_dbsr_diag_nc2, 292	fasp_solver_pvfgmres, 313
fasp_precond_dbsr_diag_nc3, 294	pvgmres.c, 314
fasp_precond_dbsr_diag_nc5, 294	fasp_solver_bdcsr_pvgmres, 315
fasp_precond_dbsr_diag_nc7, 296	fasp_solver_dbsr_pvgmres, 315
fasp_precond_dbsr_ilu, 296	fasp_solver_dcsr_pvgmres, 317
fasp_precond_dbsr_nl_amli, 298	fasp_solver_dstr_pvgmres, 318
precond_csr.c, 298	pvgmres_mf.c, 318
fasp_precond_amg, 299	fasp_solver_pvgmres, 319
fasp_precond_amli, 299	
fasp_precond_diag, 300	quadrature.c, 320
fasp_precond_famg, 300	fasp_gauss2d, 320

fasp_quad2d, 320	messages.h, 246
	SOLVER_CG
r precond_block_data, 49	messages.h, 246
precond_block_reservoir_data, 52	SOLVER_FMG
precond FASP blkoil data, 61	messages.h, 246
REAL	SOLVER_GCG
fasp.h, 147	messages.h, 247
RR	SOLVER_GMRES
precond block reservoir data, 52	messages.h, 247 SOLVER_MUMPS
precond_FASP_blkoil_data, 61	messages.h, 247
RUN_FAIL	SOLVER_MinRes
messages.h, 244	messages.h, 247
rap.c, 321	SOLVER_SBiCGstab
fasp_blas_dcsr_rap2, 321	messages.h, 247
restart	SOLVER SCG
input_param, 43	messages.h, 247
itsolver_param, 45	SOLVER_SGCG
precond_FASP_blkoil_data, 61	messages.h, 247
row_idx	SOLVER SGMRES
precond_block_data, 49	messages.h, 247
S	SOLVER_SMinRes
grid2d, 33	messages.h, 247
SA AMG	SOLVER_SUPERLU
messages.h, 245	messages.h, 248
SHORT	SOLVER_SVFGMRES
fasp.h, 147	messages.h, 248
SMALLREAL	SOLVER_SVGMRES
fasp.h, 148	messages.h, 248
SMOOTHER_BLKOIL	SOLVER_UMFPACK
messages.h, 245	messages.h, 248
SMOOTHER_CG	SOLVER_VFGMRES
messages.h, 245	messages.h, 248
SMOOTHER_GS	SOLVER_VGMRES
messages.h, 245	messages.h, 248
SMOOTHER_GSOR	SS
messages.h, 245	precond_block_reservoir_data, 52
SMOOTHER_JACOBI	precond_FASP_blkoil_data, 61
messages.h, 245	STAG_RATIO fasp.h, 148
SMOOTHER_L1DIAG	STOP_MOD_REL_RES
messages.h, 245	messages.h, 248
SMOOTHER_POLY	STOP REL PRECRES
messages.h, 245 SMOOTHER SGS	messages.h, 248
messages.h, 246	STOP_REL_RES
SMOOTHER SGSOR	messages.h, 249
messages.h, 246	SUCCESS
SMOOTHER_SOR	messages.h, 249
messages.h, 246	scaled
SMOOTHER SSOR	precond_block_reservoir_data, 52
messages.h, 246	precond_FASP_blkoil_data, 61
SOLVER_AMG	schwarz.f, 322
messages.h, 246	Schwarz_data, 62
SOLVER_BiCGstab	Schwarz_maxlvl
_	_

input_param, 43	fasp_smoother_dstr_gs, 348
Schwarz_mmsize	fasp_smoother_dstr_gs1, 349
	• — — — —
input_param, 43	fasp_smoother_dstr_gs_ascend, 349
Schwarz_param, 63	fasp_smoother_dstr_gs_cf, 350
schwarz_setup.c, 323	fasp_smoother_dstr_gs_descend, 350
fasp_schwarz_setup, 323	fasp_smoother_dstr_gs_order, 351
Schwarz_type	fasp_smoother_dstr_jacobi, 351
input_param, 43	fasp_smoother_dstr_jacobi1, 352
smat.c, 324	fasp_smoother_dstr_schwarz, 352
fasp_blas_smat_inv, 325	fasp_smoother_dstr_sor, 352
fasp_blas_smat_inv_nc2, 325	fasp_smoother_dstr_sor1, 353
fasp_blas_smat_inv_nc3, 325	fasp_smoother_dstr_sor_ascend, 353
fasp_blas_smat_inv_nc4, 326	fasp_smoother_dstr_sor_cf, 354
fasp_blas_smat_inv_nc5, 326	fasp_smoother_dstr_sor_descend, 354
fasp_blas_smat_inv_nc7, 326	fasp_smoother_dstr_sor_order, 355
fasp_iden_free, 327	solver_type
fasp_smat_identity, 327	input_param, 43
fasp_smat_identity_nc2, 327	sparse_block.c, 355
fasp_smat_identity_nc3, 329	fasp_dbsr_getblk, 356
fasp_smat_identity_nc5, 329	fasp_dbsr_getblk_dcsr, 356
fasp smat identity nc7, 329	fasp dcsr getblk, 357
smoother_bsr.c, 330	sparse_bsr.c, 357
fasp_smoother_dbsr_gs, 331	fasp_dbsr_alloc, 358
fasp_smoother_dbsr_gs1, 331	fasp dbsr cp, 359
fasp_smoother_dbsr_gs_ascend, 332	fasp_dbsr_create, 359
fasp_smoother_dbsr_gs_descend, 332	fasp_dbsr_diaginv, 360
fasp_smoother_dbsr_gs_order1, 333	fasp_dbsr_diaginv2, 360
fasp_smoother_dbsr_gs_order2, 333	fasp_dbsr_diaginv3, 360
fasp_smoother_dbsr_ilu, 334	fasp_dbsr_diaginv4, 361
fasp_smoother_dbsr_jacobi, 334	fasp_dbsr_diagpref, 361
fasp_smoother_dbsr_jacobi1, 334	. — — •
· – – –	fasp_dbsr_free, 362
fasp_smoother_dbsr_jacobi_setup, 336	fasp_dbsr_getdiag, 362
fasp_smoother_dbsr_sor, 336	fasp_dbsr_getdiaginv, 363
fasp_smoother_dbsr_sor1, 337	fasp_dbsr_null, 363
fasp_smoother_dbsr_sor_ascend, 337	fasp_dbsr_trans, 364
fasp_smoother_dbsr_sor_descend, 338	sparse_coo.c, 364
fasp_smoother_dbsr_sor_order, 338	fasp_dcoo_alloc, 365
smoother_csr.c, 339	fasp_dcoo_create, 365
fasp_smoother_dcsr_L1diag, 342	fasp_dcoo_free, 365
fasp_smoother_dcsr_gs, 340	fasp_dcoo_shift, 366
fasp_smoother_dcsr_gs_cf, 340	sparse_csr.c, 366
fasp_smoother_dcsr_ilu, 341	fasp_dcsr_alloc, 368
fasp_smoother_dcsr_jacobi, 341	fasp_dcsr_compress, 368
fasp_smoother_dcsr_kaczmarz, 342	fasp_dcsr_compress_inplace, 368
fasp_smoother_dcsr_sgs, 343	fasp_dcsr_cp, 369
fasp_smoother_dcsr_sor, 343	fasp_dcsr_create, 369
fasp_smoother_dcsr_sor_cf, 344	fasp_dcsr_diagpref, 370
smoother_csr_cr.c, 344	fasp dcsr free, 370
fasp_smoother_dcsr_gscr, 345	fasp_dcsr_getcol, 371
smoother_csr_poly.c, 346	fasp_dcsr_getdiag, 371
fasp_smoother_dcsr_poly, 346	fasp_dcsr_multicoloring, 371
fasp_smoother_dcsr_poly_old, 346	fasp_dcsr_null, 373
smoother_str.c, 347	fasp_dcsr_perm, 373
fasp_generate_diaginv_block, 348	fasp_dcsr_regdiag, 374
iasp_generate_utaginv_block, 346	iasp_ucsi_regulay, 3/4

fasp_dcsr_shift, 374	fasp_solver_dcsr_spvgmres, 408
fasp_dcsr_sort, 374	fasp_solver_dstr_spvgmres, 409
fasp_dcsr_symdiagscale, 376	stop_type
fasp_dcsr_sympat, 376	input_param, 44
fasp_dcsr_trans, 376	itsolver_param, 45
fasp_icsr_cp, 378	
fasp_icsr_create, 378	t
fasp_icsr_free, 379	grid2d, 33
fasp_icsr_null, 379	THDs_AMG_GS
fasp_icsr_trans, 379	itsolver_bsr.c, 211
sparse_csrl.c, 380	THDs_CPR_gGS
fasp_dcsrl_create, 380	itsolver_bsr.c, 211
fasp_dcsrl_free, 381	THDs_CPR_IGS
sparse_str.c, 381	itsolver_bsr.c, 211
fasp_dstr_alloc, 382	TRUE
fasp_dstr_cp, 382	messages.h, 249
fasp_dstr_create, 383	tfather
fasp_dstr_free, 383	grid2d, 34
fasp_dstr_null, 383	threads.c, 410
sparse_util.c, 384	FASP_GET_START_END, 410
fasp_sparse_MIS, 387	timing.c, 411
fasp_sparse_aat_, 385	fasp_gettime, 411
fasp_sparse_abyb_, 385	tol
fasp_sparse_abybms_, 386	itsolver_param, 45
fasp_sparse_aplbms_, 386	precond_FASP_blkoil_data, 61
fasp_sparse_aplusb_, 387	total_alloc_count
fasp_sparse_iit_, 387	fasp.h, 150
fasp_sparse_rapcmp_, 388	memory.c, 230
fasp_sparse_rapms_, 388	total_alloc_mem
fasp_sparse_wta_, 389	fasp.h, 150
fasp_sparse_wtams_, 389	memory.c, 230
fasp_sparse_ytx_, 391	triangles
fasp_sparse_ytxbig_, 391	grid2d, 34
spbcgs.c, 392	LIA AMO
fasp_solver_bdcsr_spbcgs, 393	UA_AMG
fasp_solver_dbsr_spbcgs, 394	messages.h, 249
fasp_solver_dcsr_spbcgs, 394	UNPT
fasp solver dstr spbcgs, 396	messages.h, 249
spcg.c, 397	USERDEFINED
fasp_solver_bdcsr_spcg, 398	messages.h, 249
fasp_solver_dcsr_spcg, 399	V CYCLE
fasp_solver_dstr_spcg, 399	messages.h, 249
spgmres.c, 400	val
fasp_solver_bdcsr_spgmres, 401	
fasp solver dbsr spgmres, 401	dBSRmat, 27
fasp_solver_dcsr_spgmres, 402	vec.c, 412
fasp_solver_dstr_spgmres, 402	fasp_dvec_alloc, 413
spminres.c, 403	fasp_dvec_cp, 413
fasp_solver_bdcsr_spminres, 405	fasp_dvec_create, 413
fasp_solver_dcsr_spriinres, 405	fasp_dvec_free, 414
fasp_solver_dstr_spminres, 406	fasp_dvec_isnan, 414
· – – ·	fasp_dvec_maxdiff, 414
spygmres.c, 407	fasp_dvec_null, 415
fasp_solver_bdcsr_spvgmres, 407	fasp_dvec_rand, 415
fasp_solver_dbsr_spvgmres, 408	fasp_dvec_set, 416

```
fasp_dvec_symdiagscale, 416
    fasp_ivec_alloc, 417
    fasp_ivec_create, 417
    fasp_ivec_free, 417
    fasp_ivec_set, 419
vertices
    grid2d, 34
    precond_block_reservoir_data, 52
    precond_FASP_blkoil_data, 62
W_CYCLE
    messages.h, 250
\mathsf{WW}
    precond_block_reservoir_data, 52
    precond_FASP_blkoil_data, 62
workdir
    input_param, 44
wrapper.c, 419
    fasp_fwrapper_amg_, 420
    fasp_fwrapper_krylov_amg_, 420
    fasp_wrapper_dbsr_krylov_amg, 421
    fasp_wrapper_dcoo_dbsr_krylov_amg, 421
```