Fast Auxiliary Space Preconditioning 1.4.0 Dec/25/2013

Generated by Doxygen 1.8.6

Thu Dec 26 2013 21:01:41

Contents

1	Intro	eduction Control of the Control of t	1					
2	How to obtain FASP 3							
3	Build	ding and Installation	5					
4	Deve	elopers	7					
5	Doxy	ygen	9					
6	Data	Structure Index	11					
	6.1	Data Structures	11					
7	File	Index	13					
	7.1	File List	13					
8	Data	Structure Documentation	19					
	8.1	AMG_data Struct Reference	19					
		8.1.1 Detailed Description	20					
	8.2	AMG_data_bsr Struct Reference	20					
		8.2.1 Detailed Description	21					
	8.3	AMG_param Struct Reference	21					
		8.3.1 Detailed Description	23					
	8.4	block_BSR Struct Reference	23					
		8.4.1 Detailed Description	24					
	8.5	block_dCSRmat Struct Reference	24					
		8.5.1 Detailed Description	24					
	8.6	block_dvector Struct Reference	25					
		8.6.1 Detailed Description	25					
	8.7	block_iCSRmat Struct Reference	25					
		8.7.1 Detailed Description	25					

iv CONTENTS

8.8	block_ivector Struct Reference	26
	8.8.1 Detailed Description	26
8.9	block_Reservoir Struct Reference	26
	8.9.1 Detailed Description	26
8.10	dBSRmat Struct Reference	27
	8.10.1 Detailed Description	27
	8.10.2 Field Documentation	27
	8.10.2.1 JA	27
	8.10.2.2 val	28
8.11	dCOOmat Struct Reference	28
	8.11.1 Detailed Description	28
8.12	dCSRLmat Struct Reference	29
	8.12.1 Detailed Description	29
8.13	dCSRmat Struct Reference	29
	8.13.1 Detailed Description	30
8.14	ddenmat Struct Reference	30
	8.14.1 Detailed Description	30
8.15	dSTRmat Struct Reference	31
	8.15.1 Detailed Description	31
8.16	dvector Struct Reference	31
	8.16.1 Detailed Description	32
8.17	grid2d Struct Reference	32
	8.17.1 Detailed Description	32
	8.17.2 Field Documentation	33
	8.17.2.1 e	33
	8.17.2.2 edges	33
	8.17.2.3 ediri	33
	8.17.2.4 efather	33
	8.17.2.5 p	33
	8.17.2.6 pdiri	33
	8.17.2.7 pfather	33
	8.17.2.8 s	33
	8.17.2.9 t	34
	8.17.2.10 tfather	34
	8.17.2.11 triangles	34
	8.17.2.12 vertices	34
8.18	iCOOmat Struct Reference	34

CONTENTS

	8.18.1	Detailed I	Description	
8.19	iCSRm	at Struct F	Reference	
	8.19.1	Detailed I	Description	
8.20	idenma	at Struct Re	eference	
	8.20.1	Detailed I	Description	
8.21	ILU_da	ıta Struct F	Reference	
	8.21.1	Detailed I	Description	
8.22	ILU_pa	ram Struc	t Reference	
			Description	
8.23			ct Reference	
			Description	
	8.23.2		cumentation	
			AMG_aggressive_level	
			AMG_aggressive_path	
			AMG_amli_degree	
		8.23.2.4	AMG_coarse_dof	
			AMG_coarse_scaling	
			AMG_coarsening_type	
			AMG_cycle_type	
			AMG_ILU_levels	
			AMG_interpolation_type	
			AMG_levels	
			AMG_max_aggregation	
			AMG_max_row_sum	
			AMG_maxit	
			AMG_nl_amli_krylov_type	
			AMG_polynomial_degree	
			AMG_postsmooth_iter	
			AMG_presmooth_iter	
			AMG_relaxation	
			AMG_schwarz_levels	
			AMG_smooth_filter	
			AMG_smooth_order	
			AMG_smoother	
			AMG_strong_coupled	
			AMG_strong_threshold	
		8.23.2.25	AMG_tentative_smooth	4

vi CONTENTS

		8.23.2.26 A	AMG_tol				 	 	 	 	 	٠.	42
		8.23.2.27 A	AMG_tru	ncation_	thresh	old .	 	 	 	 	 		42
		8.23.2.28 A	AMG_typ	е			 	 	 	 	 		42
		8.23.2.29 I	LU_drop	tol			 	 	 	 	 		42
		8.23.2.30 I	ILU_lfil .				 	 	 	 	 		42
		8.23.2.31 I	ILU_pern	ntol			 	 	 	 	 		42
		8.23.2.32 I	LU_relax	 .			 	 	 	 	 		42
		8.23.2.33 I	LU_type				 	 	 	 	 		42
		8.23.2.34 i	tsolver_n	naxit .			 	 	 	 	 		42
		8.23.2.35 i	tsolver_t	ol			 	 	 	 	 		43
		8.23.2.36	output_ty	pe			 	 	 	 	 		43
		8.23.2.37 p	precond_	type			 	 	 	 	 		43
		8.23.2.38 p	orint_leve	el			 	 	 	 	 		43
		8.23.2.39 p	problem_	num .			 	 	 	 	 		43
		8.23.2.40 r	restart .				 	 	 	 	 		43
		8.23.2.41	Schwarz_	_maxlvl			 	 	 	 	 		43
		8.23.2.42	Schwarz_	_mmsize			 	 	 	 	 		43
		8.23.2.43	Schwarz_	_type .			 	 	 	 	 		43
		8.23.2.44	solver_ty	oe			 	 	 	 	 		44
		8.23.2.45	stop_type				 	 	 	 	 		44
		8.23.2.46 v	workdir .				 	 	 	 	 		44
8.24	itsolver	_param Stru	uct Refer	ence .			 	 	 	 	 		44
	8.24.1	Detailed De	escription	١			 	 	 	 	 		44
	8.24.2	Field Docu	mentatio	n			 	 	 	 	 		44
		8.24.2.1 i	tsolver_t	ype			 	 	 	 	 		44
		8.24.2.2 r	maxit				 	 	 	 	 		45
		8.24.2.3 p	precond_	type			 	 	 	 	 		45
		8.24.2.4 p	print_leve	el			 	 	 	 	 		45
		8.24.2.5 r	restart .				 	 	 	 	 		45
		8.24.2.6	stop_type				 	 	 	 	 		45
		8.24.2.7 t	t ol				 	 	 	 	 		45
8.25	ivector	Struct Refer	rence				 	 	 	 	 		45
	8.25.1	Detailed De	escription	1			 	 	 	 	 		46
8.26	Link St	ruct Referen	nce				 	 	 	 	 		46
	8.26.1	Detailed De	escription	1			 	 	 	 	 		46
8.27	linked_	list Struct Re	eference				 	 	 	 	 		46
	8.27.1	Detailed De	escription	1			 	 	 	 	 		47

CONTENTS vii

8.28	8 mxv_matfree Struct Reference	47
	8.28.1 Detailed Description	47
8.29	9 precond Struct Reference	47
	8.29.1 Detailed Description	48
8.30	0 precond_block_data Struct Reference	48
	8.30.1 Detailed Description	48
	8.30.2 Field Documentation	48
	8.30.2.1 A	48
	8.30.2.2 Aarray	48
	8.30.2.3 Ablock	49
	8.30.2.4 amgparam	49
	8.30.2.5 col_idx	49
	8.30.2.6 r	49
	8.30.2.7 row_idx	
8.31	1 precond_block_reservoir_data Struct Reference	49
	8.31.1 Detailed Description	51
	8.31.2 Field Documentation	51
	8.31.2.1 diag	
	8.31.2.2 diaginv	51
	8.31.2.3 diaginvS	51
	8.31.2.4 order	51
	8.31.2.5 perf_idx	
	8.31.2.6 pivot	
	8.31.2.7 pivotS	
	8.31.2.8 PP	52
	8.31.2.9 r	52
	8.31.2.10 RR	
	8.31.2.11 scaled	52
	8.31.2.12 SS	52
	8.31.2.13 w	52
	8.31.2.14 WW	52
8.32	2 precond_data Struct Reference	52
	8.32.1 Detailed Description	54
8.33	3 precond_data_bsr Struct Reference	54
	8.33.1 Detailed Description	55
8.34	4 precond_data_str Struct Reference	55
	8.34.1 Detailed Description	57

viii CONTENTS

8.35	precon	d_diagbsr Struct Reference
	8.35.1	Detailed Description
8.36	precon	d_diagstr Struct Reference
	8.36.1	Detailed Description
8.37	precon	d_FASP_blkoil_data Struct Reference
	8.37.1	Detailed Description
	8.37.2	Field Documentation
		8.37.2.1 A
		8.37.2.2 diaginv
		8.37.2.3 diaginv_noscale
		8.37.2.4 diaginv_S
		8.37.2.5 maxit
		8.37.2.6 mgl_data
		8.37.2.7 neigh
		8.37.2.8 order
		8.37.2.9 perf_idx
		8.37.2.10 perf_neigh
		8.37.2.11 pivot
		8.37.2.12 pivot_S
		8.37.2.13 PP
		8.37.2.14 r
		8.37.2.15 restart
		8.37.2.16 RR
		8.37.2.17 scaled
		8.37.2.18 SS
		8.37.2.19 tol
		8.37.2.20 w
		8.37.2.21 WW
8.38	Schwa	rz_data Struct Reference
	8.38.1	Detailed Description
8.39	Schwa	rz_param Struct Reference
	8.39.1	Detailed Description
File	Doouma	CE .
9.1		entation 65 File Reference
J. I	9.1.1	Detailed Description
		Function Documentation
	9.1.2	runction documentation

9

CONTENTS ix

		9.1.2.1 fasp_solver_amg
9.2	amg_s	etup_aggregation_bsr.inl File Reference
	9.2.1	Detailed Description
9.3	amg_s	etup_aggregation_csr.inl File Reference
	9.3.1	Detailed Description
9.4	amg_s	etup_cr.c File Reference
	9.4.1	Detailed Description
	9.4.2	Function Documentation
		9.4.2.1 fasp_amg_setup_cr
9.5	amg_s	etup_rs.c File Reference
	9.5.1	Detailed Description
	9.5.2	Function Documentation
		9.5.2.1 fasp_amg_setup_rs
		9.5.2.2 fasp_amg_setup_rs_omp
9.6	amg_s	etup_sa.c File Reference
	9.6.1	Detailed Description
	9.6.2	Function Documentation
		9.6.2.1 fasp_amg_setup_sa
9.7	amg_s	etup_ua.c File Reference
	9.7.1	Detailed Description
	9.7.2	Function Documentation
		9.7.2.1 fasp_amg_setup_ua
		9.7.2.2 fasp_amg_setup_ua_bsr
9.8	amg_s	olve.c File Reference
	9.8.1	Detailed Description
	9.8.2	Function Documentation
		9.8.2.1 fasp_amg_solve
		9.8.2.2 fasp_amg_solve_amli
		9.8.2.3 fasp_amg_solve_nl_amli
		9.8.2.4 fasp_famg_solve
9.9	amlired	cur.c File Reference
	9.9.1	Detailed Description
	9.9.2	Function Documentation
		9.9.2.1 fasp_amg_amli_coef
		9.9.2.2 fasp_solver_amli
		9.9.2.3 fasp_solver_nl_amli
		9.9.2.4 fasp_solver_nl_amli_bsr

CONTENTS

9.10	array.c	File Refer	ence				 	 	 	 	 	 	77
	9.10.1	Detailed	Description				 	 	 	 	 	 	78
	9.10.2	Function	Documenta	ition .			 	 	 	 	 	 	78
		9.10.2.1	fasp_array	_cp .			 	 	 	 	 	 	78
		9.10.2.2	fasp_array	_cp_nc	3		 	 	 	 	 	 	78
		9.10.2.3	fasp_array	_cp_nc	:5		 	 	 	 	 	 	79
		9.10.2.4	fasp_array	_cp_nc	7		 	 	 	 	 	 	79
		9.10.2.5	fasp_array	_null .			 	 	 	 	 	 	79
		9.10.2.6	fasp_array	_set .			 	 	 	 	 	 	80
		9.10.2.7	fasp_iarray	y_cp .			 	 	 	 	 	 	80
		9.10.2.8	fasp_iarray	y_set .			 	 	 	 	 	 	81
9.11	blas_ar	ray.c File	Reference				 	 	 	 	 	 	81
	9.11.1	Detailed	Description				 	 	 	 	 	 	82
	9.11.2	Function	Documenta	ition .			 	 	 	 	 	 	82
		9.11.2.1	fasp_blas_	_array_a	ax		 	 	 	 	 	 	82
		9.11.2.2	fasp_blas_	_array_a	axpby		 	 	 	 	 	 	82
		9.11.2.3	fasp_blas_	_array_a	axpy .		 	 	 	 	 	 	83
		9.11.2.4	fasp_blas_	_array_a	axpyz .		 	 	 	 	 	 	83
		9.11.2.5	fasp_blas_	_array_c	dotprod	l	 	 	 	 	 	 	84
		9.11.2.6	fasp_blas_	_array_r	norm1		 	 	 	 	 	 	84
		9.11.2.7	fasp_blas_	_array_r	norm2		 	 	 	 	 	 	85
		9.11.2.8	fasp_blas_	_array_r	norminf	f	 	 	 	 	 	 	85
9.12	blas_bo	csr.c File F	Reference				 	 	 	 	 	 	86
	9.12.1	Detailed	Description				 	 	 	 	 	 	86
	9.12.2	Function	Documenta	ıtion .			 	 	 	 	 	 	87
		9.12.2.1	fasp_blas_	_bdbsr_	аАхру		 	 	 	 	 	 	87
		9.12.2.2	fasp_blas_	_bdbsr_	mxv .		 	 	 	 	 	 	88
		9.12.2.3	fasp_blas_	_bdcsr_	аАхру		 	 	 	 	 	 	88
		9.12.2.4	fasp_blas_	_bdcsr_	mxv .		 	 	 	 	 	 	89
9.13	blas_bs	sr.c File Re	eference .				 	 	 	 	 	 	89
	9.13.1	Detailed	Description				 	 	 	 	 	 	89
	9.13.2	Function	Documenta	ıtion .			 	 	 	 	 	 	90
		9.13.2.1	fasp_blas_	_dbsr_a	Axpby		 	 	 	 	 	 	90
		9.13.2.2	fasp_blas_	_dbsr_a	Ахру .		 	 	 	 	 	 	91
		9.13.2.3	fasp_blas_	_dbsr_m	nxv		 	 	 	 	 	 	92
		9.13.2.4	fasp_blas_	_dbsr_ra	ар		 	 	 	 	 	 	93
		9.13.2.5	fasp_blas_	_dbsr_ra	ар1		 	 	 	 	 	 	93

CONTENTS xi

9.14 blas_csr.c File Reference	94
9.14.1 Detailed Description	95
9.14.2 Function Documentation	95
9.14.2.1 fasp_blas_dcsr_aAxpy	95
9.14.2.2 fasp_blas_dcsr_aAxpy_agg	96
9.14.2.3 fasp_blas_dcsr_add	96
9.14.2.4 fasp_blas_dcsr_axm	96
9.14.2.5 fasp_blas_dcsr_mxm	97
9.14.2.6 fasp_blas_dcsr_mxv	97
9.14.2.7 fasp_blas_dcsr_mxv_agg	98
9.14.2.8 fasp_blas_dcsr_ptap	98
9.14.2.9 fasp_blas_dcsr_rap	99
9.14.2.10 fasp_blas_dcsr_rap4	99
9.14.2.11 fasp_blas_dcsr_rap_agg	00
9.14.2.12 fasp_blas_dcsr_rap_agg1	00
9.14.2.13 fasp_blas_dcsr_vmv	01
9.15 blas_csrl.c File Reference	01
9.15.1 Detailed Description	02
9.15.2 Function Documentation	02
9.15.2.1 fasp_blas_dcsrl_mxv	02
9.16 blas_smat.c File Reference	02
9.16.1 Detailed Description	04
9.16.2 Function Documentation	04
9.16.2.1 fasp_blas_array_axpy_nc2	04
9.16.2.2 fasp_blas_array_axpy_nc3	04
9.16.2.3 fasp_blas_array_axpy_nc5	05
9.16.2.4 fasp_blas_array_axpy_nc7	05
9.16.2.5 fasp_blas_array_axpyz_nc2	05
9.16.2.6 fasp_blas_array_axpyz_nc3	06
9.16.2.7 fasp_blas_array_axpyz_nc5	06
9.16.2.8 fasp_blas_array_axpyz_nc7	07
9.16.2.9 fasp_blas_smat_aAxpby	07
9.16.2.10 fasp_blas_smat_mul	80
9.16.2.11 fasp_blas_smat_mul_nc2	80
9.16.2.12 fasp_blas_smat_mul_nc3	09
9.16.2.13 fasp_blas_smat_mul_nc5	09
9.16.2.14 fasp_blas_smat_mul_nc7	09

xii CONTENTS

9.	16.2.15 fasp_blas_smat_mxv	10
9.	16.2.16 fasp_blas_smat_mxv_nc2	10
9.	16.2.17 fasp_blas_smat_mxv_nc3	11
9.	16.2.18 fasp_blas_smat_mxv_nc5	12
9.	16.2.19 fasp_blas_smat_mxv_nc7	12
9.	16.2.20 fasp_blas_smat_ymAx	13
9.	16.2.21 fasp_blas_smat_ymAx_nc2	14
9.	16.2.22 fasp_blas_smat_ymAx_nc3	14
9.	16.2.23 fasp_blas_smat_ymAx_nc5	15
9.	16.2.24 fasp_blas_smat_ymAx_nc7	15
9.	16.2.25 fasp_blas_smat_ymAx_ns	16
9.	16.2.26 fasp_blas_smat_ymAx_ns2	16
9.	16.2.27 fasp_blas_smat_ymAx_ns3	17
9.	16.2.28 fasp_blas_smat_ymAx_ns5	17
9.	16.2.29 fasp_blas_smat_ymAx_ns7	18
9.	16.2.30 fasp_blas_smat_ypAx	18
9.	16.2.31 fasp_blas_smat_ypAx_nc2	19
9.	16.2.32 fasp_blas_smat_ypAx_nc3	19
9.	16.2.33 fasp_blas_smat_ypAx_nc5	20
9.	16.2.34 fasp_blas_smat_ypAx_nc7	21
9.17 blas_str.c	File Reference	21
9.17.1 De	etailed Description	22
9.17.2 Fu	unction Documentation	22
9.	17.2.1 fasp_blas_dstr_aAxpy	22
9.	17.2.2 fasp_blas_dstr_mxv	22
9.	17.2.3 fasp_dstr_diagscale	22
9.18 blas_vec.d	File Reference	23
9.18.1 De	etailed Description	23
9.18.2 Fu	unction Documentation	24
9.	18.2.1 fasp_blas_dvec_axpy	24
9.	18.2.2 fasp_blas_dvec_axpyz	24
9.	18.2.3 fasp_blas_dvec_dotprod	24
9.	18.2.4 fasp_blas_dvec_norm1	25
9.	18.2.5 fasp_blas_dvec_norm2	25
9.	18.2.6 fasp_blas_dvec_norminf	26
9.	18.2.7 fasp_blas_dvec_relerr	26
9.19 checkmat.	c File Reference	27

CONTENTS xiii

	9.19.1	Detailed Description
	9.19.2	Function Documentation
		9.19.2.1 fasp_check_dCSRmat
		9.19.2.2 fasp_check_diagdom
		9.19.2.3 fasp_check_diagpos
		9.19.2.4 fasp_check_diagzero
		9.19.2.5 fasp_check_iCSRmat
		9.19.2.6 fasp_check_symm
9.20	coarser	ning_cr.c File Reference
	9.20.1	Detailed Description
	9.20.2	Function Documentation
		9.20.2.1 fasp_amg_coarsening_cr
9.21	coarser	ning_rs.c File Reference
	9.21.1	Detailed Description
	9.21.2	Function Documentation
		9.21.2.1 fasp_amg_coarsening_rs
9.22	convert	c.c File Reference
	9.22.1	Detailed Description
	9.22.2	Function Documentation
		9.22.2.1 endian_convert_int
		9.22.2.2 endian_convert_real
		9.22.2.3 fasp_aux_bbyteToldouble
		9.22.2.4 fasp_aux_change_endian4
		9.22.2.5 fasp_aux_change_endian8
9.23	doxyge	n.h File Reference
	9.23.1	Detailed Description
9.24	eigen.c	File Reference
	9.24.1	Detailed Description
	9.24.2	Function Documentation
		9.24.2.1 fasp_dcsr_eig
9.25	factor.f	File Reference
	9.25.1	Detailed Description
9.26	famg.c	File Reference
	9.26.1	Detailed Description
	9.26.2	Function Documentation
		9.26.2.1 fasp_solver_famg
9.27	fasp.h F	File Reference

xiv CONTENTS

9.27.1	Detailed Description	1
9.27.2	Macro Definition Documentation	1
	9.27.2.1FASP_HEADER	1
	9.27.2.2 ABS	5
	9.27.2.3 BIGREAL	5
	9.27.2.4 C2N	5
	9.27.2.5 CHMEM_MODE	5
	9.27.2.6 DEBUG_MODE	5
	9.27.2.7 DIAGONAL_PREF	5
	9.27.2.8 DLMALLOC	5
	9.27.2.9 FASP_GSRB145	5
	9.27.2.10 FASP_USE_ILU	3
	9.27.2.11 GE	3
	9.27.2.12 GT	3
	9.27.2.13 INT	ŝ
	9.27.2.14 ISNAN	ŝ
	9.27.2.15 ISTART	3
	9.27.2.16 LE	ŝ
	9.27.2.17 LONG	3
	9.27.2.18 LONGLONG	7
	9.27.2.19 LS	7
	9.27.2.20 MAX	7
	9.27.2.21 MAX_AMG_LVL	7
	9.27.2.22 MAX_REFINE_LVL	7
	9.27.2.23 MAX_RESTART	7
	9.27.2.24 MAX_STAG	7
	9.27.2.25 MIN	7
	9.27.2.26 N2C	3
	9.27.2.27 NEDMALLOC	3
	9.27.2.28 OPENMP_HOLDS	3
	9.27.2.29 REAL	3
	9.27.2.30 RS_C1	3
	9.27.2.31 SHORT	3
	9.27.2.32 SMALLREAL	3
	9.27.2.33 STAG_RATIO	3
9.27.3	Typedef Documentation	9
	9.27.3.1 dCOOmat	Э

CONTENTS xv

	9.27.3.2 dCSRLmat
	9.27.3.3 dCSRmat
	9.27.3.4 ddenmat
	9.27.3.5 dSTRmat
	9.27.3.6 dvector
	9.27.3.7 grid2d
	9.27.3.8 iCOOmat
	9.27.3.9 iCSRmat
	9.27.3.10 idenmat
	9.27.3.11 ivector
	9.27.3.12 LinkList
	9.27.3.13 ListElement
	9.27.3.14 pcgrid2d
	9.27.3.15 pgrid2d
9.27.4	Variable Documentation
	9.27.4.1 IMAP
	9.27.4.2 MAXIMAP
	9.27.4.3 nx_rb
	9.27.4.4 ny_rb
	9.27.4.5 nz_rb
	9.27.4.6 total_alloc_count
	9.27.4.7 total_alloc_mem
9.28 fasp_b	olock.h File Reference
9.28.1	Detailed Description
9.28.2	Typedef Documentation
	9.28.2.1 block_BSR
	9.28.2.2 block_dCSRmat
	9.28.2.3 block_dvector
	9.28.2.4 block_iCSRmat
	9.28.2.5 block_ivector
	9.28.2.6 block_Reservoir
	9.28.2.7 dBSRmat
	9.28.2.8 precond_block_reservoir_data
9.29 fmgcy	cle.c File Reference
9.29.1	Detailed Description
9.29.2	Function Documentation
	9.29.2.1 fasp_solver_fmgcycle

xvi CONTENTS

9.30 format	s.c File Reference
9.30.1	Detailed Description
9.30.2	Function Documentation
	9.30.2.1 fasp_format_bdcsr_dcsr
	9.30.2.2 fasp_format_dbsr_dcoo
	9.30.2.3 fasp_format_dbsr_dcsr
	9.30.2.4 fasp_format_dcoo_dcsr
	9.30.2.5 fasp_format_dcsr_dbsr
	9.30.2.6 fasp_format_dcsr_dcoo
	9.30.2.7 fasp_format_dcsrl_dcsr
	9.30.2.8 fasp_format_dstr_dbsr
	9.30.2.9 fasp_format_dstr_dcsr
9.31 givens	.c File Reference
9.31.1	Detailed Description
9.31.2	Function Documentation
	9.31.2.1 fasp_aux_givens
9.32 gmg_p	poisson.c File Reference
9.32.1	Detailed Description
9.32.2	Function Documentation
	9.32.2.1 fasp_poisson_fgmg_1D
	9.32.2.2 fasp_poisson_fgmg_2D
	9.32.2.3 fasp_poisson_fgmg_3D
	9.32.2.4 fasp_poisson_gmg_1D
	9.32.2.5 fasp_poisson_gmg_2D
	9.32.2.6 fasp_poisson_gmg_3D
	9.32.2.7 fasp_poisson_pcg_gmg_1D
	9.32.2.8 fasp_poisson_pcg_gmg_2D
	9.32.2.9 fasp_poisson_pcg_gmg_3D
9.33 gmg_u	ıtil.inl File Reference
9.33.1	Detailed Description
9.34 graphi	cs.c File Reference
9.34.1	Detailed Description
9.34.2	Function Documentation
	9.34.2.1 fasp_dbsr_plot
	9.34.2.2 fasp_dcsr_subplot
	9.34.2.3 fasp_grid2d_plot
9.35 ilu.f Fil	e Reference

CONTENTS xvii

	9.35.1	Detailed Description	168
9.36	ilu_setu	ıp_bsr.c File Reference	168
	9.36.1	Detailed Description	168
	9.36.2	Function Documentation	169
		9.36.2.1 fasp_ilu_dbsr_setup	169
9.37	ilu_setu	ıp_csr.c File Reference	170
	9.37.1	Detailed Description	170
	9.37.2	Function Documentation	170
		9.37.2.1 fasp_ilu_dcsr_setup	170
9.38	ilu_setu	p_str.c File Reference	171
	9.38.1	Detailed Description	171
	9.38.2	Function Documentation	171
		9.38.2.1 fasp_ilu_dstr_setup0	
		9.38.2.2 fasp_ilu_dstr_setup1	
9.39	init.c Fi	le Reference	172
		Detailed Description	
	9.39.2	Function Documentation	173
		9.39.2.1 fasp_amg_data_bsr_create	
		9.39.2.2 fasp_amg_data_bsr_free	
		9.39.2.3 fasp_amg_data_create	
		9.39.2.4 fasp_amg_data_free	
		9.39.2.5 fasp_ilu_data_alloc	
		9.39.2.6 fasp_ilu_data_free	
		9.39.2.7 fasp_ilu_data_null	
		9.39.2.8 fasp_precond_null	176
		9.39.2.9 fasp_schwarz_data_free	
9.40		File Reference	
		Detailed Description	
	9.40.2	Function Documentation	177
		9.40.2.1 fasp_param_input	177
9.41	interfac	e_mumps.c File Reference	177
		Detailed Description	
	9.41.2	Function Documentation	
		9.41.2.1 fasp_solver_mumps	
		9.41.2.2 fasp_solver_mumps_steps	
9.42		e_samg.c File Reference	
	9.42.1	Detailed Description	179

xviii CONTENTS

	9.42.2	Function Documentation
		9.42.2.1 dCSRmat2SAMGInput
		9.42.2.2 dvector2SAMGInput
9.43	interfac	e_superlu.c File Reference
	9.43.1	Detailed Description
	9.43.2	Function Documentation
		9.43.2.1 fasp_solver_superlu
9.44	interfac	e_umfpack.c File Reference
	9.44.1	Detailed Description
	9.44.2	Function Documentation
		9.44.2.1 fasp_solver_umfpack
9.45	interpo	lation.c File Reference
	9.45.1	Detailed Description
	9.45.2	Function Documentation
		9.45.2.1 fasp_amg_interp
		9.45.2.2 fasp_amg_interp1
		9.45.2.3 fasp_amg_interp_trunc
9.46	interpo	lation_em.c File Reference
	9.46.1	Detailed Description
	9.46.2	Function Documentation
		9.46.2.1 fasp_amg_interp_em
9.47	io.c File	e Reference
	9.47.1	Detailed Description
	9.47.2	Function Documentation
		9.47.2.1 fasp_dbsr_print
		9.47.2.2 fasp_dbsr_read
		9.47.2.3 fasp_dbsr_write
		9.47.2.4 fasp_dbsr_write_coo
		9.47.2.5 fasp_dcoo1_read
		9.47.2.6 fasp_dcoo_print
		9.47.2.7 fasp_dcoo_read
		9.47.2.8 fasp_dcoo_write
		9.47.2.9 fasp_dcsr_print
		9.47.2.10 fasp_dcsr_read
		9.47.2.11 fasp_dcsrvec1_read
		9.47.2.12 fasp_dcsrvec1_write
		9.47.2.13 fasp_dcsrvec2_read

CONTENTS xix

		9.47.2.14 fasp_dcsrvec2_write
		9.47.2.15 fasp_dmtx_read
		9.47.2.16 fasp_dmtxsym_read
		9.47.2.17 fasp_dstr_print
		9.47.2.18 fasp_dstr_read
		9.47.2.19 fasp_dstr_write
		9.47.2.20 fasp_dvec_print
		9.47.2.21 fasp_dvec_read
		9.47.2.22 fasp_dvec_write
		9.47.2.23 fasp_dvecind_read
		9.47.2.24 fasp_dvecind_write
		9.47.2.25 fasp_ivec_print
		9.47.2.26 fasp_ivec_read
		9.47.2.27 fasp_ivec_write
		9.47.2.28 fasp_ivecind_read
		9.47.2.29 fasp_matrix_read
		9.47.2.30 fasp_matrix_read_bin
		9.47.2.31 fasp_matrix_write
		9.47.2.32 fasp_vector_read
		9.47.2.33 fasp_vector_write
9.48	itsolver	_bcsr.c File Reference
	9.48.1	Detailed Description
	9.48.2	Function Documentation
		9.48.2.1 fasp_solver_bdcsr_itsolver
		9.48.2.2 fasp_solver_bdcsr_krylov
9.49	itsolver	_bsr.c File Reference
	9.49.1	Detailed Description
	9.49.2	Function Documentation
		9.49.2.1 fasp_set_GS_threads
		9.49.2.2 fasp_solver_dbsr_itsolver
		9.49.2.3 fasp_solver_dbsr_krylov
		9.49.2.4 fasp_solver_dbsr_krylov_amg
		9.49.2.5 fasp_solver_dbsr_krylov_diag
		9.49.2.6 fasp_solver_dbsr_krylov_ilu
	9.49.3	Variable Documentation
		9.49.3.1 THDs_AMG_GS
		9.49.3.2 THDs_CPR_gGS

XX CONTENTS

		9.49.3.3 THDs_CPR_IGS	10
9.50	itsolver	_csr.c File Reference	10
	9.50.1	Detailed Description	11
	9.50.2	Function Documentation	11
		9.50.2.1 fasp_solver_dcsr_itsolver	11
		9.50.2.2 fasp_solver_dcsr_krylov	12
		9.50.2.3 fasp_solver_dcsr_krylov_amg	12
		9.50.2.4 fasp_solver_dcsr_krylov_diag	13
		9.50.2.5 fasp_solver_dcsr_krylov_ilu	13
		9.50.2.6 fasp_solver_dcsr_krylov_ilu_M	14
		9.50.2.7 fasp_solver_dcsr_krylov_schwarz	14
9.51	itsolver	_mf.c File Reference	15
	9.51.1	Detailed Description	15
	9.51.2	Function Documentation	16
		9.51.2.1 fasp_solver_itsolver	16
		9.51.2.2 fasp_solver_itsolver_init	17
		9.51.2.3 fasp_solver_krylov	17
9.52	itsolver	_str.c File Reference	18
	9.52.1	Detailed Description	19
	9.52.2	Function Documentation	19
		9.52.2.1 fasp_solver_dstr_itsolver	19
		9.52.2.2 fasp_solver_dstr_krylov	19
		9.52.2.3 fasp_solver_dstr_krylov_blockgs	20
		9.52.2.4 fasp_solver_dstr_krylov_diag	20
		9.52.2.5 fasp_solver_dstr_krylov_ilu	21
9.53	itsolver	_util.inl File Reference	21
	9.53.1	Detailed Description	22
9.54	linklist.i	nl File Reference	22
	9.54.1	Detailed Description	22
	9.54.2	Macro Definition Documentation	22
		9.54.2.1 LIST_HEAD	22
		9.54.2.2 LIST_TAIL	22
9.55	lu.c File	Reference	23
	9.55.1	Detailed Description	23
	9.55.2	Function Documentation	23
		9.55.2.1 fasp_smat_lu_decomp	23
		9.55.2.2 fasp_smat_lu_solve	24

CONTENTS xxi

9.56	memor	y.c File Ref	ference	24
	9.56.1	Detailed D	Description	25
	9.56.2	Function [Documentation	25
		9.56.2.1	fasp_mem_check	25
		9.56.2.2	fasp_mem_dcsr_check	25
		9.56.2.3	fasp_mem_free	26
		9.56.2.4	fasp_mem_iludata_check	26
		9.56.2.5	fasp_mem_realloc	27
		9.56.2.6	fasp_mem_usage	27
	9.56.3	Variable D	Occumentation	27
		9.56.3.1	total_alloc_count	27
		9.56.3.2	total_alloc_mem	28
9.57	messag	ge.c File Re	eference	28
	9.57.1	Detailed D	Description	28
	9.57.2	Function [Documentation	28
		9.57.2.1	fasp_chkerr	28
		9.57.2.2	print_amgcomplexity	29
		9.57.2.3	print_amgcomplexity_bsr	29
		9.57.2.4	print_cputime	29
		9.57.2.5	print_itinfo	:30
		9.57.2.6	print_message	:30
9.58	messag	ges.h File F	Reference	:31
	9.58.1	Detailed D	Description	:34
	9.58.2		finition Documentation	
		9.58.2.1	AMLI_CYCLE	:34
		9.58.2.2	ASCEND	:34
		9.58.2.3	CF_ORDER	:34
		9.58.2.4	CGPT	:34
		9.58.2.5	CLASSIC_AMG	:34
		9.58.2.6	COARSE_AC	:34
		9.58.2.7	COARSE_CR	:35
		9.58.2.8	COARSE_RS	:35
		9.58.2.9	CPFIRST	:35
		9.58.2.10	DESCEND	:35
		9.58.2.11	ERROR_ALLOC_MEM	:35
		9.58.2.12	ERROR_AMG_COARSE_TYPE	:35
		9.58.2.13	ERROR_AMG_COARSEING	235

xxii CONTENTS

9.58.2.14 ERROR_AMG_INTERP_TYPE	
9.58.2.15 ERROR_AMG_SMOOTH_TYPE	
9.58.2.16 ERROR_DATA_STRUCTURE	
9.58.2.17 ERROR_DATA_ZERODIAG	
9.58.2.18 ERROR_DUMMY_VAR	
9.58.2.19 ERROR_INPUT_PAR	
9.58.2.20 ERROR_MISC	
9.58.2.21 ERROR_NUM_BLOCKS	
9.58.2.22 ERROR_OPEN_FILE	
9.58.2.23 ERROR_QUAD_DIM	
9.58.2.24 ERROR_QUAD_TYPE	
9.58.2.25 ERROR_REGRESS	
9.58.2.26 ERROR_SOLVER_EXIT	
9.58.2.27 ERROR_SOLVER_ILUSETUP	
9.58.2.28 ERROR_SOLVER_MAXIT	
9.58.2.29 ERROR_SOLVER_MISC	
9.58.2.30 ERROR_SOLVER_PRECTYPE	
9.58.2.31 ERROR_SOLVER_SOLSTAG	
9.58.2.32 ERROR_SOLVER_STAG	
9.58.2.33 ERROR_SOLVER_TOLSMALL	
9.58.2.34 ERROR_SOLVER_TYPE	
9.58.2.35 ERROR_WRONG_FILE	
9.58.2.36 FALSE	
9.58.2.37 FGPT	
9.58.2.38 FPFIRST	
9.58.2.39 ILUk	
9.58.2.40 ILUt	
9.58.2.41 ILUtp	
9.58.2.42 INTERP_DIR	
9.58.2.43 INTERP_ENG	
9.58.2.44 INTERP_STD	
9.58.2.45 ISPT	
9.58.2.46 MAT_bBSR	
9.58.2.47 MAT_bCSR	
9.58.2.48 MAT_BSR	
9.58.2.49 MAT_CSR	
9.58.2.50 MAT_CSRL	

CONTENTS xxiii

9.58.2.51 MAT_FREE	
9.58.2.52 MAT_STR	240
9.58.2.53 MAT_SymCSR	240
9.58.2.54 NL_AMLI_CYCLE	240
9.58.2.55 NO_ORDER	240
9.58.2.56 OFF	241
9.58.2.57 ON	241
9.58.2.58 PREC_AMG	241
9.58.2.59 PREC_DIAG	241
9.58.2.60 PREC_FMG	241
9.58.2.61 PREC_ILU	241
9.58.2.62 PREC_NULL	241
9.58.2.63 PREC_SCHWARZ	241
9.58.2.64 PRINT_ALL	242
9.58.2.65 PRINT_MIN	242
9.58.2.66 PRINT_MORE	242
9.58.2.67 PRINT_MOST	242
9.58.2.68 PRINT_NONE	242
9.58.2.69 PRINT_SOME	242
9.58.2.70 RUN_FAIL	242
9.58.2.71 SA_AMG	
9.58.2.72 SMOOTHER_BLKOIL	243
9.58.2.73 SMOOTHER_CG	
9.58.2.74 SMOOTHER_GS	243
9.58.2.75 SMOOTHER_GSOR	243
9.58.2.76 SMOOTHER_JACOBI	243
9.58.2.77 SMOOTHER_L1DIAG	
9.58.2.78 SMOOTHER_POLY	243
9.58.2.79 SMOOTHER_SGS	243
9.58.2.80 SMOOTHER_SGSOR	244
9.58.2.81 SMOOTHER_SOR	244
9.58.2.82 SMOOTHER_SSOR	244
9.58.2.83 SOLVER_AMG	244
9.58.2.84 SOLVER_BiCGstab	244
9.58.2.85 SOLVER_CG	244
9.58.2.86 SOLVER_FMG	
9.58.2.87 SOLVER_GCG	244

xxiv CONTENTS

		9.58.2.88 SOLVER_GMRES
		9.58.2.89 SOLVER_MinRes
		9.58.2.90 SOLVER_MUMPS
		9.58.2.91 SOLVER_SBiCGstab
		9.58.2.92 SOLVER_SCG
		9.58.2.93 SOLVER_SGCG
		9.58.2.94 SOLVER_SGMRES
		9.58.2.95 SOLVER_SMinRes
		9.58.2.96 SOLVER_SUPERLU
		9.58.2.97 SOLVER_SVFGMRES
		9.58.2.98 SOLVER_SVGMRES
		9.58.2.99 SOLVER_UMFPACK
		9.58.2.100SOLVER_VFGMRES
		9.58.2.101SOLVER_VGMRES
		9.58.2.102STOP_MOD_REL_RES
		9.58.2.103STOP_REL_PRECRES
		9.58.2.104STOP_REL_RES
		9.58.2.105SUCCESS
		9.58.2.106TRUE
		9.58.2.107UA_AMG
		9.58.2.108UNPT
		9.58.2.109USERDEFINED
		9.58.2.110V_CYCLE
		9.58.2.111W_CYCLE
9.59	mg_util	inl File Reference
	9.59.1	Detailed Description
9.60	mgcycl	e.c File Reference
	9.60.1	Detailed Description
	9.60.2	Function Documentation
		9.60.2.1 fasp_solver_mgcycle
		9.60.2.2 fasp_solver_mgcycle_bsr
9.61	mgrecu	r.c File Reference
	9.61.1	Detailed Description
	9.61.2	Function Documentation
		9.61.2.1 fasp_solver_mgrecur
9.62	orderin	g.c File Reference
	9.62.1	Detailed Description

CONTENTS XXV

	9.62.2	Function	Documentation	. 251
		9.62.2.1	fasp_aux_dQuickSort	. 251
		9.62.2.2	fasp_aux_dQuickSortIndex	. 252
		9.62.2.3	fasp_aux_iQuickSort	. 252
		9.62.2.4	fasp_aux_iQuickSortIndex	. 253
		9.62.2.5	fasp_aux_merge	. 253
		9.62.2.6	fasp_aux_msort	. 254
		9.62.2.7	fasp_aux_unique	. 254
		9.62.2.8	fasp_BinarySearch	. 255
9.63	parame	eters.c File	Reference	. 255
	9.63.1	Detailed I	Description	. 256
	9.63.2		Documentation	
		9.63.2.1	fasp_param_amg_init	. 257
			fasp_param_amg_print	
		9.63.2.3	fasp_param_amg_set	. 258
			fasp_param_amg_to_prec	
		9.63.2.5	fasp_param_amg_to_prec_bsr	. 259
		9.63.2.6	fasp_param_ilu_init	. 259
		9.63.2.7	fasp_param_ilu_print	. 259
		9.63.2.8	fasp_param_ilu_set	. 260
		9.63.2.9	fasp_param_init	. 260
			fasp_param_input_init	
			fasp_param_prec_to_amg	
			fasp_param_prec_to_amg_bsr	
		9.63.2.13	fasp_param_schwarz_init	. 262
		9.63.2.14	fasp_param_schwarz_print	. 262
		9.63.2.15	fasp_param_schwarz_set	. 262
		9.63.2.16	fasp_param_solver_init	. 263
		9.63.2.17	fasp_param_solver_print	. 263
			fasp_param_solver_set	
		9.63.2.19	fasp_precond_data_null	. 264
9.64	pbcgs.d	File Refe	rence	. 264
	9.64.1	Detailed I	Description	. 265
	9.64.2		Documentation	
		9.64.2.1	fasp_solver_bdcsr_pbcgs	. 266
		9.64.2.2	fasp_solver_dbsr_pbcgs	. 266
		9.64.2.3	fasp_solver_dcsr_pbcgs	. 267

xxvi CONTENTS

9.64.2.4 fasp_solver_dstr_pbcgs
9.65 pbcgs_mf.c File Reference
9.65.1 Detailed Description
9.65.2 Function Documentation
9.65.2.1 fasp_solver_pbcgs
9.66 pcg.c File Reference
9.66.1 Detailed Description
9.66.2 Function Documentation
9.66.2.1 fasp_solver_bdcsr_pcg
9.66.2.2 fasp_solver_dcsr_pcg
9.66.2.3 fasp_solver_dstr_pcg
9.67 pcg_mf.c File Reference
9.67.1 Detailed Description
9.67.2 Function Documentation
9.67.2.1 fasp_solver_pcg
9.68 pgcg.c File Reference
9.68.1 Detailed Description
9.68.2 Function Documentation
9.68.2.1 fasp_solver_dcsr_pgcg
9.69 pgcg_mf.c File Reference
9.69.1 Detailed Description
9.69.2 Function Documentation
9.69.2.1 fasp_solver_pgcg
9.70 pgmres.c File Reference
9.70.1 Detailed Description
9.70.2 Function Documentation
9.70.2.1 fasp_solver_bdcsr_pgmres
9.70.2.2 fasp_solver_dbsr_pgmres
9.70.2.3 fasp_solver_dcsr_pgmres
9.70.2.4 fasp_solver_dstr_pgmres
9.71 pgmres_mf.c File Reference
9.71.1 Detailed Description
9.71.2 Function Documentation
9.71.2.1 fasp_solver_pgmres
9.72 pminres.c File Reference
9.72.1 Detailed Description
9.72.2 Function Documentation

CONTENTS xxvii

		9.72.2.1	fasp_solver_bdcsr_pminres	. 285
		9.72.2.2	fasp_solver_dcsr_pminres	. 286
		9.72.2.3	fasp_solver_dstr_pminres	. 286
9.73	pminres	s_mf.c File	Reference	. 287
	9.73.1	Detailed D	Description	. 287
	9.73.2	Function D	Documentation	. 288
		9.73.2.1	fasp_solver_pminres	. 288
9.74	precond	d_bsr.c File	Reference	. 289
	9.74.1	Detailed D	Pescription	. 290
	9.74.2	Function D	Documentation	. 290
		9.74.2.1	fasp_precond_dbsr_amg	. 290
		9.74.2.2	fasp_precond_dbsr_diag	. 290
		9.74.2.3	fasp_precond_dbsr_diag_nc2	. 291
		9.74.2.4	fasp_precond_dbsr_diag_nc3	. 292
		9.74.2.5	fasp_precond_dbsr_diag_nc5	. 293
		9.74.2.6	fasp_precond_dbsr_diag_nc7	. 294
		9.74.2.7	fasp_precond_dbsr_ilu	. 295
		9.74.2.8	fasp_precond_dbsr_nl_amli	. 296
9.75	precond	d_csr.c File	Reference	. 296
	9.75.1	Detailed D	Description	. 297
	9.75.2	Function D	Documentation	. 297
		9.75.2.1	fasp_precond_amg	. 297
		9.75.2.2	fasp_precond_amli	. 298
		9.75.2.3	fasp_precond_diag	. 298
		9.75.2.4	fasp_precond_famg	. 298
		9.75.2.5	fasp_precond_free	. 299
		9.75.2.6	fasp_precond_ilu	. 299
		9.75.2.7	fasp_precond_ilu_backward	. 299
		9.75.2.8	fasp_precond_ilu_forward	. 300
		9.75.2.9	fasp_precond_nl_amli	. 300
		9.75.2.10	fasp_precond_schwarz	. 301
		9.75.2.11	fasp_precond_setup	. 302
9.76	precond	d_str.c File	Reference	. 302
	9.76.1	Detailed D	Description	. 303
	9.76.2	Function D	Documentation	. 303
		9.76.2.1	fasp_precond_dstr_blockgs	. 303
		9.76.2.2	fasp_precond_dstr_diag	. 303

xxviii CONTENTS

		9.76.2.3	fasp_precond_e	dstr_ilu0			 	 	 	 	. 304
		9.76.2.4	fasp_precond_o	dstr_ilu0_	_backwa	rd	 	 	 	 	. 304
		9.76.2.5	fasp_precond_o	dstr_ilu0_	_forward		 	 	 	 	. 305
		9.76.2.6	fasp_precond_o	dstr_ilu1			 	 	 	 	. 306
		9.76.2.7	fasp_precond_o	dstr_ilu1_	_backwa	rd	 	 	 	 	. 306
		9.76.2.8	fasp_precond_o	dstr_ilu1_	_forward		 	 	 	 	. 307
9.77	pvfgmr	es.c File R	eference				 	 	 	 	. 308
	9.77.1	Detailed [Description				 	 	 	 	. 308
	9.77.2	Function	Documentation				 	 	 	 	. 309
		9.77.2.1	fasp_solver_db	sr_pvfgm	ires		 	 	 	 	. 309
			fasp_solver_dc								
9.78	pvfgmr	es_mf.c Fil	le Reference				 	 	 	 	. 311
	9.78.1	Detailed I	Description				 	 	 	 	. 311
	9.78.2		Documentation								
			fasp_solver_pv	_							
9.79	pvgmre	es.c File Re	eference				 	 	 	 	. 312
	9.79.1	Detailed [Description				 	 	 	 	. 313
	9.79.2	Function	Documentation				 	 	 	 	. 313
			fasp_solver_bd								
			fasp_solver_db								
			fasp_solver_dc								
			fasp_solver_ds								
	. •	_	e Reference								
			Description								
	9.80.2		Documentation								
			fasp_solver_pv								
			Reference								
			Description								
	9.81.2		Documentation								
			fasp_gauss2d								
			fasp_quad2d .								
			nce								
			Description								
	9.82.2		Documentation								
			fasp_blas_dcsr								
			ference								
	9.83.1	Detailed I	Description				 	 	 	 	. 320

CONTENTS xxix

9.84	schwar	z_setup.c File Reference	21
	9.84.1	Detailed Description	21
	9.84.2	Function Documentation	21
		9.84.2.1 fasp_schwarz_setup	21
9.85	smat.c	File Reference	22
	9.85.1	Detailed Description	23
	9.85.2	Function Documentation	23
		9.85.2.1 fasp_blas_smat_inv	23
		9.85.2.2 fasp_blas_smat_inv_nc2	23
		9.85.2.3 fasp_blas_smat_inv_nc3	23
		9.85.2.4 fasp_blas_smat_inv_nc4	24
		9.85.2.5 fasp_blas_smat_inv_nc5	24
		9.85.2.6 fasp_blas_smat_inv_nc7	24
		9.85.2.7 fasp_iden_free	25
		9.85.2.8 fasp_smat_identity	25
		9.85.2.9 fasp_smat_identity_nc2	26
		9.85.2.10 fasp_smat_identity_nc3	27
		9.85.2.11 fasp_smat_identity_nc5	27
		9.85.2.12 fasp_smat_identity_nc7	27
9.86	smooth	er_bsr.c File Reference	28
	9.86.1	Detailed Description	29
	9.86.2	Function Documentation	29
		9.86.2.1 fasp_smoother_dbsr_gs	29
		9.86.2.2 fasp_smoother_dbsr_gs1	29
		9.86.2.3 fasp_smoother_dbsr_gs_ascend	30
		9.86.2.4 fasp_smoother_dbsr_gs_descend	30
		9.86.2.5 fasp_smoother_dbsr_gs_order1	31
		9.86.2.6 fasp_smoother_dbsr_gs_order2	31
		9.86.2.7 fasp_smoother_dbsr_ilu	32
		9.86.2.8 fasp_smoother_dbsr_jacobi	32
		9.86.2.9 fasp_smoother_dbsr_jacobi1	33
		9.86.2.10 fasp_smoother_dbsr_jacobi_setup	34
		9.86.2.11 fasp_smoother_dbsr_sor	34
		9.86.2.12 fasp_smoother_dbsr_sor1	35
		9.86.2.13 fasp_smoother_dbsr_sor_ascend	35
		9.86.2.14 fasp_smoother_dbsr_sor_descend	36
		9.86.2.15 fasp_smoother_dbsr_sor_order	36

CONTENTS

9.87	smooth	er_csr.c Fi	ile Reference				 	 	 	 	 	337
	9.87.1	Detailed [Description .				 	 	 	 	 	338
	9.87.2	Function	Documentation	٠			 	 	 	 	 	338
		9.87.2.1	fasp_smoothe	r_dcsr_	_gs		 	 	 	 	 	338
		9.87.2.2	fasp_smoothe	r_dcsr_	_gs_cf		 	 	 	 	 	338
		9.87.2.3	fasp_smoothe	r_dcsr_	_ilu		 	 	 	 	 	339
		9.87.2.4	fasp_smoothe	r_dcsr_	_jacobi		 	 	 	 	 	339
		9.87.2.5	fasp_smoothe	r_dcsr_	_kaczm	arz .	 	 	 	 	 	340
		9.87.2.6	fasp_smoothe	r_dcsr_	_L1diag	j	 	 	 	 	 	340
		9.87.2.7	fasp_smoothe	r_dcsr_	_sgs .		 	 	 	 	 	341
		9.87.2.8	fasp_smoothe	r_dcsr_	_sor		 	 	 	 	 	341
		9.87.2.9	fasp_smoothe	r_dcsr_	_sor_cf		 	 	 	 	 	342
9.88	smooth	er_csr_cr.	c File Referenc	e			 	 	 	 	 	342
	9.88.1	Detailed [Description .				 	 	 	 	 	343
	9.88.2	Function	Documentation	٠			 	 	 	 	 	343
		9.88.2.1	fasp_smoothe	r_dcsr_	_gscr .		 	 	 	 	 	343
9.89	smooth	er_csr_po	ly.c File Refere	nce .			 	 	 	 	 	344
	9.89.1	Detailed [Description .				 	 	 	 	 	344
	9.89.2	Function	Documentation	١			 	 	 	 	 	344
		9.89.2.1	fasp_smoothe	r_dcsr_	_poly .		 	 	 	 	 	344
		9.89.2.2	fasp_smoothe	r_dcsr_	_poly_o	old	 	 	 	 	 	344
9.90	smooth	er_str.c Fil	le Reference				 	 	 	 	 	345
	9.90.1	Detailed [Description .				 	 	 	 	 	346
	9.90.2	Function	Documentation	٠			 	 	 	 	 	346
		9.90.2.1	fasp_generate	e_diagir	nv_bloc	k	 	 	 	 	 	346
		9.90.2.2	fasp_smoothe	r_dstr_	_gs		 	 	 	 	 	346
		9.90.2.3	fasp_smoothe	r_dstr_	gs1		 	 	 	 	 	347
		9.90.2.4	fasp_smoothe	r_dstr_	gs_asc	end .	 	 	 	 	 	347
		9.90.2.5	fasp_smoothe	r_dstr_	gs_cf .		 	 	 	 	 	348
		9.90.2.6	fasp_smoothe	r_dstr_	gs_des	scend	 	 	 	 	 	348
		9.90.2.7	fasp_smoothe	r_dstr_	_gsord	ler	 	 	 	 	 	349
		9.90.2.8	fasp_smoothe	r_dstr_	jacobi		 	 	 	 	 	349
		9.90.2.9	fasp_smoothe	r_dstr_	jacobi1		 	 	 	 	 	350
		9.90.2.10	fasp_smoothe	r_dstr_	schwar	rz	 	 	 	 	 	350
		9.90.2.11	fasp_smoothe	r_dstr_	sor		 	 	 	 	 	350
		9.90.2.12	fasp_smoothe	r_dstr_	sor1 .		 	 	 	 	 	351
		9.90.2.13	fasp_smoothe	r_dstr_	sor_as	cend	 	 	 	 	 	351

CONTENTS xxxi

		9.90.2.14	4 fas	sp_sn	nooth	er_d	str_s	sor_	_cf			 	 	 	 	 	 	 . 352
		9.90.2.15	5 fas	sp_sn	nooth	er_d	str_s	sor_	des	cenc	١	 	 	 	 	 	 	 . 352
		9.90.2.16	6 fas	sp_sn	nooth	er_d	str_s	sor_	orde	er .		 	 	 	 	 	 	 . 353
9.91	sparse	_block.c Fi	ile F	Refere	ence							 	 	 	 	 	 	 . 353
	9.91.1	Detailed [Des	cripti	on .							 	 	 	 	 	 	 . 354
	9.91.2	Function	Doo	cume	ntatio	n .						 	 	 	 	 	 	 . 354
		9.91.2.1	fas	sp_db	osr_ge	etblk						 	 	 	 	 	 	 . 354
		9.91.2.2	fas	sp_db	osr_ge	etblk	_dcs	r.				 	 	 	 	 	 	 . 354
		9.91.2.3	fas	sp_dc	sr_ge	etblk						 	 	 	 	 	 	 . 355
9.92	sparse	_bsr.c File	Re	feren	ce							 	 	 	 	 	 	 . 355
	9.92.1	Detailed [Des	cripti	on .							 	 	 	 	 	 	 . 356
	9.92.2	Function	Doo	cume	ntatio	n .						 	 	 	 	 	 	 . 356
		9.92.2.1	fas	sp_db	osr_all	loc						 	 	 	 	 	 	 . 356
		9.92.2.2	fas	sp_db	osr_cp)						 	 	 	 	 	 	 . 357
		9.92.2.3	fas	sp_db	osr_cr	eate						 	 	 	 	 	 	 . 357
		9.92.2.4	fas	sp_db	osr_dia	agin	v .					 	 	 	 	 	 	 . 358
		9.92.2.5	fas	sp_db	osr_dia	agin	v2					 	 	 	 	 	 	 . 358
		9.92.2.6	fas	sp_db	osr_dia	agin	v3					 	 	 	 	 	 	 . 358
		9.92.2.7	fas	sp_db	osr_dia	agin	v4					 	 	 	 	 	 	 . 359
		9.92.2.8	fas	sp_db	osr_dia	agpr	ef					 	 	 	 	 	 	 . 359
		9.92.2.9	fas	sp_db	osr_fre	эе .						 	 	 	 	 	 	 . 360
		9.92.2.10) fas	sp_db	osr_ge	etdia	g.					 	 	 	 	 	 	 . 360
		9.92.2.11	1 fas	sp_db	osr_ge	etdia	ginv					 	 	 	 	 	 	 . 361
		9.92.2.12	2 fas	sp_db	osr_nu	. الد						 	 	 	 	 	 	 . 361
		9.92.2.13	3 fas	sp_db	osr_tra	ans						 	 	 	 	 	 	 . 362
9.93	sparse	_coo.c File	e Re	eferen	ice .							 	 	 	 	 	 	 . 362
	9.93.1	Detailed [Des	cripti	on .							 	 	 	 	 	 	 . 363
	9.93.2	Function	Doo	cume	ntatio	n .						 	 	 	 	 	 	 . 363
		9.93.2.1	fas	sp_dc	oo_al	lloc						 	 	 	 	 	 	 . 363
		9.93.2.2	fas	sp_dc	00_0	reate	.					 	 	 	 	 	 	 . 363
		9.93.2.3	fas	sp_dc	oo_fr	ee						 	 	 	 	 	 	 . 363
		9.93.2.4	fas	sp_dc	:00_sl	hift						 	 	 	 	 	 	 . 364
9.94	sparse	_csr.c File	Ref	feren	ce							 	 	 	 	 	 	 . 364
	9.94.1	Detailed I	Des	cripti	on .							 	 	 	 	 	 	 . 365
	9.94.2	Function	Doo	cume	ntatio	n .						 	 	 	 	 	 	 . 366
		9.94.2.1	fas	sp_dc	sr_all	loc						 	 	 	 	 	 	 . 366
		9.94.2.2	fas	sp_dc	sr_co	mpr	ess					 	 	 	 	 	 	 . 366

xxxii CONTENTS

		9.94.2.3 tasp_dcsr_compress_inplace	366
		9.94.2.4 fasp_dcsr_cp	367
		9.94.2.5 fasp_dcsr_create	367
		9.94.2.6 fasp_dcsr_diagpref	368
		9.94.2.7 fasp_dcsr_free	368
		9.94.2.8 fasp_dcsr_getcol	369
		9.94.2.9 fasp_dcsr_getdiag	369
		9.94.2.10 fasp_dcsr_multicoloring	370
		9.94.2.11 fasp_dcsr_null	371
		9.94.2.12 fasp_dcsr_perm	371
		9.94.2.13 fasp_dcsr_regdiag	372
		9.94.2.14 fasp_dcsr_shift	372
		9.94.2.15 fasp_dcsr_sort	373
		9.94.2.16 fasp_dcsr_symdiagscale	374
		9.94.2.17 fasp_dcsr_sympat	374
		9.94.2.18 fasp_dcsr_trans	375
		9.94.2.19 fasp_icsr_cp	376
		9.94.2.20 fasp_icsr_create	376
		9.94.2.21 fasp_icsr_free	377
		9.94.2.22 fasp_icsr_null	377
		9.94.2.23 fasp_icsr_trans	377
9.95	sparse_	csrl.c File Reference	378
	9.95.1	Detailed Description	378
	9.95.2	Function Documentation	378
		9.95.2.1 fasp_dcsrl_create	378
		9.95.2.2 fasp_dcsrl_free	379
9.96	sparse_	str.c File Reference	379
	9.96.1	Detailed Description	380
	9.96.2	Function Documentation	380
		9.96.2.1 fasp_dstr_alloc	380
		9.96.2.2 fasp_dstr_cp	380
		9.96.2.3 fasp_dstr_create	381
		9.96.2.4 fasp_dstr_free	381
		9.96.2.5 fasp_dstr_null	381
9.97	sparse_	util.c File Reference	382
	9.97.1	Detailed Description	383
	9.97.2	Function Documentation	383

CONTENTS xxxiii

	9.97.2.1 fasp_sparse_aat
	9.97.2.2 fasp_sparse_abyb
	9.97.2.3 fasp_sparse_abybms
	9.97.2.4 fasp_sparse_aplbms
	9.97.2.5 fasp_sparse_aplusb
	9.97.2.6 fasp_sparse_iit
	9.97.2.7 fasp_sparse_MIS
	9.97.2.8 fasp_sparse_rapcmp
	9.97.2.9 fasp_sparse_rapms
	9.97.2.10 fasp_sparse_wta
	9.97.2.11 fasp_sparse_wtams
	9.97.2.12 fasp_sparse_ytx
	9.97.2.13 fasp_sparse_ytxbig
	gs.c File Reference
9.98.	1 Detailed Description
9.98.	Function Documentation
	9.98.2.1 fasp_solver_bdcsr_spbcgs
	9.98.2.2 fasp_solver_dbsr_spbcgs
	9.98.2.3 fasp_solver_dcsr_spbcgs
	9.98.2.4 fasp_solver_dstr_spbcgs
9.99 spcg.	c File Reference
9.99.	1 Detailed Description
9.99.	2 Function Documentation
	9.99.2.1 fasp_solver_bdcsr_spcg
	9.99.2.2 fasp_solver_dcsr_spcg
	9.99.2.3 fasp_solver_dstr_spcg
9.100spgm	res.c File Reference
9.100	.1 Detailed Description
9.100	.2 Function Documentation
	9.100.2.1 fasp_solver_bdcsr_spgmres
	9.100.2.2 fasp_solver_dbsr_spgmres
	9.100.2.3 fasp_solver_dcsr_spgmres
	9.100.2.4 fasp_solver_dstr_spgmres
9.101spmir	nres.c File Reference
9.101	.1 Detailed Description
9.101	.2 Function Documentation
	9.101.2.1 fasp_solver_bdcsr_spminres

XXXIV CONTENTS

9.101.2.2 fasp_solver_dcsr_spminres
9.101.2.3 fasp_solver_dstr_spminres
9.102spvgmres.c File Reference
9.102.1 Detailed Description
9.102.2 Function Documentation
9.102.2.1 fasp_solver_bdcsr_spvgmres
9.102.2.2 fasp_solver_dbsr_spvgmres
9.102.2.3 fasp_solver_dcsr_spvgmres
9.102.2.4 fasp_solver_dstr_spvgmres
9.103threads.c File Reference
9.103.1 Detailed Description
9.103.2 Function Documentation
9.103.2.1 FASP_GET_START_END
9.104timing.c File Reference
9.104.1 Detailed Description
9.104.2 Function Documentation
9.104.2.1 fasp_gettime
9.105vec.c File Reference
9.105.1 Detailed Description
9.105.2 Function Documentation
9.105.2.1 fasp_dvec_alloc
9.105.2.2 fasp_dvec_cp
9.105.2.3 fasp_dvec_create
9.105.2.4 fasp_dvec_free
9.105.2.5 fasp_dvec_isnan
9.105.2.6 fasp_dvec_maxdiff
9.105.2.7 fasp_dvec_null
9.105.2.8 fasp_dvec_rand
9.105.2.9 fasp_dvec_set
9.105.2.10fasp_dvec_symdiagscale
9.105.2.11fasp_ivec_alloc
9.105.2.12fasp_ivec_create
9.105.2.13fasp_ivec_free
9.105.2.14fasp_ivec_set
9.106wrapper.c File Reference
9.106.1 Detailed Description
9.106.2 Function Documentation

ndex	4	21
	9.106.2.4 fasp_wrapper_dcoo_dbsr_krylov_amg	20
	9.106.2.3 fasp_wrapper_dbsr_krylov_amg	19
	9.106.2.2 fasp_fwrapper_krylov_amg	19
	9.106.2.1 fasp_fwrapper_amg	18
	0.100.0.1 food furcings and	1

xxxv

CONTENTS

Introduction

Over the last few decades, researchers have expended significant effort on developing efficient iterative methods for solving discretized partial differential equations (PDEs). Though these efforts have yielded many mathematically optimal solvers such as the multigrid method, the unfortunate reality is that multigrid methods have not been much used in practical applications. This marked gap between theory and practice is mainly due to the fragility of traditional multigrid (MG) methodology and the complexity of its implementation. We aim to develop techniques and the corresponding software that will narrow this gap, specifically by developing mathematically optimal solvers that are robust and easy to use in practice.

We believe that there is no one-size-for-all solution method for discrete linear systemsfrom different applications. And, efficient iterative solvers can be constructed by taking the properties of PDEs and discretizations into account. In this project, we plan to construct a pool of discrete problems arising from partial differential equations (PDEs) or PDE systems and efficient linear solvers for these problems. We mainly utilize the methodology of Auxiliary Space Preconditioning (ASP) to construct efficient linear solvers. Due to this reason, this software package is called Fast Auxiliary Space Preconditioning or FASP for short.

FASP contains the kernel part and several applications (ranging from fluid dynamics to reservoir simulation). The kernel part is open-source and licensed under GNU Lesser General Public License or LGPL version 3.0 or later. Some of the applications contain contributions from and owned partially by other parties.

For the moment, FASP is under alpha testing. If you wish to obtain a current version of FASP or you have any questions, feel free to contact us at faspdev@gmail.com.

This software distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

2	Introduction

How to obtain FASP

For the moment, FASP is still under alpha testing. You need a password to download the package. Sorry about it!

The most updated version of FASP can be downloaded from

```
http://fasp.sourceforge.net/download/faspsolver.zip
```

We use HG (Mecurial) as our main version control tool. HG is easy to use and it is available at all OS platforms. For people who is interested in the developer version, you can obtain the FASP package with hg:

\$ hg clone https://faspusers@bitbucket.org/fasp/faspsolver

will give you the developer version of the FASP package.

How to obtain FASP

Building and Installation

This is a simple instruction on building and testing. For more details, please refer to the README files and the short User's Guide in "faspsolver/doc/".

To compile, you need a Fortran and a C compiler. First, you can type in the "faspsolver/" root directory:

\$ make config

which will config the environment automatically. And, then, you can need to type:

\$ make install

which will make the FASP shared static library and install to PREFIX/. By default, FASP libraries and executables will be installed in the FASP home directory "faspsolver/".

There is a simple GUI tool for building and installing FASP included in the package. You need Tcl/Tk support in your computer. You may call this GUI by run in the root directory:

\$ wish fasp install.tcl

If you need to see the detailed usage of "make" or need any help, please type:

\$ make help

After installation, tutorial examples can be found in "tutorial/".

Building and Installatio	Buildin	a and	Instal	lation
---------------------------------	---------	-------	--------	--------

Developers

Project Leader:

• Xu, Jinchao (Penn State University, USA)

Current Developers (in alphabetic order):

- Feng, Chunsheng (Xiangtan University, China)
- Hu, Xiaozhe (Penn State University, USA)
- Li, Zheng (Xiangtan University, China)
- Shu, Shi (Xiangtan University, China)
- Wang, Ziteng (Peking University, China)
- Yue, Xiaoqiang (Xiangtan University, China)
- Zhang, Chensong (Chinese Academy of Sciences, China)
- Zikatanov, Ludmil (Penn State University, USA)

With contributions from (in alphabetic order):

- · Brannick, James (Penn State University, USA)
- · Cao, Fei (Penn State University, USA)
- Huang, Feiteng (Sichuang University, China)
- · Huang, Xuehai (Shanghai Jiaotong University, China)
- Qiao, Changhe (Penn State University, USA)
- Yang, Kai (Penn State University, USA)
- Zhang, Shiquan (Sichuan University, China)
- Zhang, Shuo (Chinese Academy of Sciences, China)
- Zhang, Weifeng (Kunming University of Science and Technology, China)

8 Developers

• Zhou, Zhiyang (Xiangtan University, China)

Project Coordinator:

• Zhang, Chensong (Chinese Academy of Sciences, China)

Doxygen

We use Doxygen as our automatically documentation generator which will make our future maintainance minimized. You can obtain the software (Windows, Linux and OS X) as well as its manual on the official website

http://www.doxygen.org

For an oridinary user, Doxygen is completely trivial to use. We only need to use some special marker in the usual comment as we put in c-files.



Data Structure Index

6.1 Data Structures

Here are the data structures with brief descriptions:

AMG_data	
Data for AMG solvers	19
AMG_data_bsr	
Data for multigrid levels. (BSR format)	20
AMG_param	
Parameters for AMG solver	21
block_BSR	
Block REAL matrix format for reservoir simulation	23
block_dCSRmat	•
Block REAL CSR matrix format	24
block_dvector Block REAL vector structure	0.5
block iCSRmat	20
Block INT CSR matrix format	25
block ivector	20
Block INT vector structure	26
block Reservoir	
Block REAL matrix format for reservoir simulation	26
dBSRmat	
Block sparse row storage matrix of REAL type	27
dCOOmat	
Sparse matrix of REAL type in COO (or IJ) format	28
dCSRLmat	
Sparse matrix of REAL type in CSRL format	29
dCSRmat	
Sparse matrix of REAL type in CSR format	29
ddenmat	
Dense matrix of REAL type	30
dSTRmat	04
Structure matrix of REAL type	31
Vector with n entries of REAL type	21
grid2d	ا ق
Two dimensional grid data structure	30
Two dimensional grid data structure	02

12 Data Structure Index

iCOOmat		
iCSRmat	-1	34
IOSHIIIai		35
idenmat		
	Dense matrix of INT type	36
ILU_data		
	Data for ILU setup	36
ILU_para	m	
		37
input_pai		
	Last Last and a second a second and a second a second and	37
itsolver_p		
	Parameters passed to iterative solvers	44
ivector	And the second s	
	Vector with n entries of INT type	45
Link		
المعالما		46
linked_lis		40
mana a maat		46
mxv_mat		47
procend	Matrix-vector multiplication, replace the actual matrix	47
precond	Preconditioner data and action	47
procend	block_data	47
precond_		48
nrecond	block reservoir data	40
procoria_		49
precond	· · · · · · · · · · · · · · · · · · ·	70
procenta_		52
precond	data_bsr	Ŭ-
p. 000u_		54
precond		•
_	· -	55
precond_		
		57
precond_	•	
		57
precond_	FASP_blkoil_data	
_		58
Schwarz_	· · · · · · · · · · · · · · · · · · ·	
	Data for Schwarz methods	62
Schwarz_	_param	
	Parameters for Schwarz method	63

File Index

7.1 File List

Here is a list of all documented files with brief descriptions:

amg.c		
	AMG method as an iterative solver (main file)	65
amg_set	up_aggregation_bsr.inl	
	Utilies for multigrid cycles in BSR format	66
amg_set	up_aggregation_csr.inl	
	Utilies for multigrid cycles for CSR matrices	66
amg_set	• —	
	Brannick-Falgout compatible relaxation based AMG: SETUP phase	66
amg_set		
	Ruge-Stuben AMG: SETUP phase	67
amg_set	•—	
	Smoothed aggregation AMG: SETUP phase	69
amg_set		70
	Unsmoothed aggregation AMG: SETUP phase	70
amg_solv		74
omliroou	Algebraic multigrid iterations: SOLVE phase	/ 1
amlirecui	Abstract AMLI multilevel iteration – recursive version	74
array.c	Austract Afficial multilever iteration – recursive version	74
array.c	Array operations	77
blas_arra	• •	' '
Diao_arro	BLAS operations for arrays	81
blas bcs		•
	BLAS operations for block_dCSRmat matrices	86
blas bsr.		
_	BLAS operations for dBSRmat matrices	89
blas_csr.	C	
	BLAS operations for dCSRmat matrices	94
blas_csrl		
	BLAS operations for dCSRLmat matrices	01
blas_sma	at.c	
	BLAS operations for small full matrix	02
blas_str.o		
	BLAS operations for dSTRmat matrices	21

14 File Index

blas_vec.	
	BLAS operations for vectors
checkmat	.c Check matrix properties
coarsenir	
	Coarsening with Brannick-Falgout strategy
coarsenir	ig_rs.c Coarsening with a modified Ruge-Stuben strategy
convert.c	Some utilities for format conversion
doxygen.l	h
eigen.c	Main page for Doygen documentation
	Simple subroutines for compute the extreme eigenvalues
factor.f	LU factoraization for CSR matrix
famg.c	Full AMG method as an iterative solver (main file)
fasp.h	Main header file for FASP
fasp_bloc	k.h
fmgcycle.	Main header file for FASP (block matrices)
formats.c	Abstract non-recursive full multigrid cycle
	Matrix format conversion routines
givens.c	Givens transformation
gmg_pois	
gmg_util.i	inl
graphics.	Routines for GMG solvers
	Functions for graphical output
ilu.f	ILU routines for preconditioning adapted from SPARSEKIT
ilu_setup __	_bsr.c Setup Incomplete LU decomposition for dBSRmat matrices
ilu_setup	
ilu_setup_	_str.c
init.c	Setup of ILU decomposition for dSTRmat matrices
input.c	Initialize important data structures
	Read input parameters
	_mumps.c Interface to MUMPS direct solvers
interface_	
interface_	superlu.c
	Interface to SuperLU direct solvers
	Interface to UMFPACK direct solvers

7.1 File List

interpolation.c
Interpolation operators for AMG
interpolation_em.c
Interpolation operators for AMG based on energy-min
io.c
Matrix-vector input/output subroutines
itsolver_bcsr.c
Iterative solvers for block_dCSRmat matrices
itsolver_bsr.c
Iterative solvers for dBSRmat matrices
itsolver_csr.c
Iterative solvers for dCSRmat matrices
itsolver_mf.c
Iterative solvers with matrix-free spmv
itsolver_str.c
Iterative solvers for dSTRmat matrices
itsolver_util.inl
Routines for iterative solvers
linklist.inl
Utilies for link list data structure
lu.c
LU decomposition and direct solve for dense matrix
memory.c
Memory allocation and deallocation
message.c
Output some useful messages
messages.h
Definition of all kinds of messages, including error messages, solver types, etc
mg_util.inl
Routines for algebraic multigrid cycles
mgcycle.c
Abstract non-recursive multigrid cycle
mgrecur.c
Abstract multigrid cycle – recursive version
ordering.c
A collection of ordering, merging, removing duplicated integers functions
parameters.c
Initialize, set, or print input data and parameters
pbcgs.c
Krylov subspace methods – Preconditioned BiCGstab
pbcgs_mf.c
Krylov subspace methods – Preconditioned BiCGstab (matrix free)
pcg.c
Krylov subspace methods – Preconditioned conjugate gradient
pcg_mf.c
Krylov subspace methods – Preconditioned conjugate gradient (matrix free)
pgcg.c
Krylov subspace methods – Preconditioned Generalized CG
pgcg_mf.c
Krylov subspace methods – Preconditioned Generalized CG (matrix free)
pgmres.c
Krylov subspace methods – Preconditioned GMRes
pgmres_mf.c
Krylov subspace methods – Preconditioned GMRes (matrix free)

16 File Index

pminres.c
Krylov subspace methods – Preconditioned minimal residual
pminres_mf.c Krylov subspace methods – Preconditioned minimal residual (matrix free)
precond_bsr.c
Preconditioners for dBSRmat matrices
precond_csr.c
Preconditioners for dCSRmat matrices
precond_str.c
Preconditioners for dSTRmat matrices
Krylov subspace methods – Preconditioned variable-restarting flexible GMRes
pvfgmres_mf.c
Krylov subspace methods – Preconditioned variable-restarting flexible GMRes (matrix free) 31
pvgmres.c
Krylov subspace methods – Preconditioned variable-restart GMRes
pvgmres_mf.c Krylov subspace methods – Preconditioned variable-restarting GMRes (matrix free)
quadrature.c
Quadrature rules
rap.c
R*A*P driver
Schwarz.f Schwarz smoothers
schwarz_setup.c
Setup phase for the Schwarz methods
smat.c
Simple operations for <i>small</i> full matrices in row-major format
smoother_bsr.c
Smoothers for dBSRmat matrices
Smoothers for dCSRmat matrices
smoother_csr_cr.c
Smoothers for dCSRmat matrices using compatible relaxation
smoother_csr_poly.c
Smoothers for dCSRmat matrices using poly. approx. to A^{-1}
smoother_str.c Smoothers for dSTRmat matrices
sparse_block.c
Sparse matrix block operations
sparse_bsr.c
Sparse matrix operations for dBSRmat matrices
sparse_coo.c
Sparse matrix operations for dCOOmat matrices
sparse_csr.c Sparse matrix operations for dCSRmat matrices
sparse_csrl.c
Sparse matrix operations for dCSRLmat matrices
sparse_str.c
Sparse matrix operations for dSTRmat matrices
sparse_util.c Routines for sparse matrix operations
spbcgs.c
Krylov subspace methods – Preconditioned BiCGstab with safe net

7.1 File List

spcg.c	
	Krylov subspace methods – Preconditioned conjugate gradient with safe net
spgmres	.c
	Krylov subspace methods – Preconditioned GMRes with safe net
spminres	3.C
	Krylov subspace methods – Preconditioned minimal residual with safe net
spvgmre	S.C
	Krylov subspace methods – Preconditioned variable-restart GMRes with safe net
threads.c	
	Get and set number of threads and assigne work load for each thread
timing.c	
	Timing subroutines
vec.c	
	Simple operations for vectors
wrapper.	C
	Wrappers for accessing functions by advanced users

18	File Index

Data Structure Documentation

8.1 AMG_data Struct Reference

Data for AMG solvers.

```
#include <fasp.h>
```

Data Fields

SHORT max_levels

max number of levels

· SHORT num levels

number of levels in use <= max levels

dCSRmat A

pointer to the matrix at level level_num

dCSRmat R

restriction operator at level level_num

dCSRmat P

prolongation operator at level level_num

dvector b

pointer to the right-hand side at level level_num

dvector x

pointer to the iterative solution at level level_num

· ivector cfmark

pointer to the CF marker at level level_num

• INT ILU_levels

number of levels use ILU smoother

• ILU_data LU

ILU matrix for ILU smoother.

· INT near kernel dim

dimension of the near kernel for SAMG

REAL ** near_kernel_basis

basis of near kernel space for SAMG

INT schwarz_levels

number of levels use schwarz smoother

• Schwarz_data schwarz

data of Schwarz smoother

· dvector w

Temporary work space.

8.1.1 Detailed Description

Data for AMG solvers.

Note

This is needed for the AMG solver/preconditioner.

Definition at line 630 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.2 AMG_data_bsr Struct Reference

Data for multigrid levels. (BSR format)

```
#include <fasp_block.h>
```

Data Fields

INT max_levels

max number of levels

• INT num_levels

number of levels in use <= max_levels

· dBSRmat A

pointer to the matrix at level level_num

• dBSRmat R

restriction operator at level level_num

dBSRmat P

prolongation operator at level level_num

dvector b

pointer to the right-hand side at level level_num

dvector x

pointer to the iterative solution at level level_num

dvector diaginv

pointer to the diagonal inverse at level level_num

dCSRmat Ac

pointer to the matrix at level level_num (csr format)

dCSRmat PP

pointer to the pressure block (only for reservoir simulation)

• REAL * pw

pointer to the auxiliary vectors for pressure block

dBSRmat SS

pointer to the saturation block (only for reservoir simulation)

REAL * sw

pointer to the auxiliary vectors for saturation block

· dvector diaginv SS

pointer to the diagonal inverse of the saturation block at level level_num

• ILU_data PP_LU

ILU data for pressure block.

· ivector cfmark

pointer to the CF marker at level level num

· INT ILU levels

number of levels use ILU smoother

• ILU_data LU

ILU matrix for ILU smoother.

• INT near_kernel_dim

dimension of the near kernel for SAMG

• REAL ** near kernel basis

basis of near kernel space for SAMG

· dvector w

temporary work space

8.2.1 Detailed Description

Data for multigrid levels. (BSR format)

Note

This structure is needed for the AMG solver/preconditioner in BSR format

Definition at line 191 of file fasp block.h.

The documentation for this struct was generated from the following file:

· fasp block.h

8.3 AMG_param Struct Reference

Parameters for AMG solver.

```
#include <fasp.h>
```

Data Fields

SHORT AMG_type

type of AMG method

SHORT print_level

print level for AMG

INT maxit

max number of iterations of AMG

REAL tol

stopping tolerance for AMG solver

SHORT max_levels

max number of levels of AMG

· INT coarse dof

max coarsest level dof

SHORT cycle_type

type of AMG cycle

· SHORT smoother

smoother type

• SHORT smooth_order

smoother order

SHORT presmooth_iter

number of presmoothers

SHORT postsmooth_iter

number of postsmoothers

· REAL relaxation

relaxation parameter for SOR smoother

SHORT polynomial_degree

degree of the polynomial smoother

· SHORT coarse_scaling

switch of scaling of the coarse grid correction

SHORT amli_degree

degree of the polynomial used by AMLI cycle

· REAL * amli coef

coefficients of the polynomial used by AMLI cycle

SHORT nl_amli_krylov_type

type of krylov method used by Nonlinear AMLI cycle

SHORT coarsening_type

coarsening type

• SHORT interpolation_type

interpolation type

REAL strong_threshold

strong connection threshold for coarsening

REAL max_row_sum

maximal row sum parameter

REAL truncation_threshold

truncation threshold

INT aggressive_level

number of levels use aggressive coarsening

INT aggressive_path

numebr of paths use to determin stongly coupled C points

REAL strong_coupled

strong coupled threshold for aggregate

• INT max_aggregation

max size of each aggregate

· REAL tentative smooth

relaxation parameter for smoothing the tentative prolongation

· SHORT smooth_filter

switch for filtered matrix used for smoothing the tentative prolongation

SHORT ILU_levels

number of levels use ILU smoother

SHORT ILU_type

ILU type for smoothing.

INT ILU_Ifil

level of fill-in for ILUs and ILUk

REAL ILU_droptol

drop tolerence for ILUt

REAL ILU_relax

relaxiation for ILUs

· REAL ILU permtol

permuted if permtol*|a(i,j)| > |a(i,i)|

· INT schwarz levels

number of levels use schwarz smoother

• INT schwarz_mmsize

maximal block size

INT schwarz_maxlvl

maximal levels

INT schwarz_type

type of schwarz method

8.3.1 Detailed Description

Parameters for AMG solver.

Note

This is needed for the AMG solver/preconditioner.

Definition at line 506 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.4 block_BSR Struct Reference

Block REAL matrix format for reservoir simulation.

#include <fasp_block.h>

Data Fields

dBSRmat ResRes

reservoir-reservoir block

dCSRmat ResWel

reservoir-well block

dCSRmat WelRes

well-reservoir block

dCSRmat WelWel

well-well block

8.4.1 Detailed Description

Block REAL matrix format for reservoir simulation.

Definition at line 165 of file fasp_block.h.

The documentation for this struct was generated from the following file:

· fasp_block.h

8.5 block_dCSRmat Struct Reference

Block REAL CSR matrix format.

```
#include <fasp_block.h>
```

Data Fields

• INT brow

row number of blocks in A, m

INT bcol

column number of blocks A, n

dCSRmat ** blocks

blocks of dCSRmat, point to blocks[brow][bcol]

8.5.1 Detailed Description

Block REAL CSR matrix format.

Note

The starting index of A is 0.

Definition at line 77 of file fasp_block.h.

The documentation for this struct was generated from the following file:

• fasp_block.h

8.6 block_dvector Struct Reference

Block REAL vector structure.

```
#include <fasp_block.h>
```

Data Fields

• INT brow

row number of blocks in A, m

dvector ** blocks

blocks of dvector, point to blocks[brow]

8.6.1 Detailed Description

Block REAL vector structure.

Definition at line 113 of file fasp_block.h.

The documentation for this struct was generated from the following file:

· fasp_block.h

8.7 block_iCSRmat Struct Reference

Block INT CSR matrix format.

```
#include <fasp_block.h>
```

Data Fields

INT brow

row number of blocks in A, m

INT bcol

column number of blocks A, n

iCSRmat ** blocks

blocks of iCSRmat, point to blocks[brow][bcol]

8.7.1 Detailed Description

Block INT CSR matrix format.

Note

The starting index of A is 0.

Definition at line 96 of file fasp_block.h.

The documentation for this struct was generated from the following file:

• fasp_block.h

8.8 block_ivector Struct Reference

Block INT vector structure.

```
#include <fasp_block.h>
```

Data Fields

• INT brow

row number of blocks in A, m

ivector ** blocks

blocks of dvector, point to blocks[brow]

8.8.1 Detailed Description

Block INT vector structure.

Note

The starting index of A is 0.

Definition at line 129 of file fasp_block.h.

The documentation for this struct was generated from the following file:

· fasp_block.h

8.9 block_Reservoir Struct Reference

Block REAL matrix format for reservoir simulation.

```
#include <fasp_block.h>
```

Data Fields

dSTRmat ResRes

reservoir-reservoir block

dCSRmat ResWel

reservoir-well block

dCSRmat WelRes

well-reservoir block

dCSRmat WelWel

well-well block

8.9.1 Detailed Description

Block REAL matrix format for reservoir simulation.

Definition at line 144 of file fasp_block.h.

The documentation for this struct was generated from the following file:

· fasp_block.h

8.10 dBSRmat Struct Reference

Block sparse row storage matrix of REAL type.

```
#include <fasp_block.h>
```

Data Fields

INT ROW

number of rows of sub-blocks in matrix A, M

INT COL

number of cols of sub-blocks in matrix A, N

INT NNZ

number of nonzero sub-blocks in matrix A, NNZ

• INT nb

dimension of each sub-block

INT storage_manner

storage manner for each sub-block

- REAL * val
- INT * IA

integer array of row pointers, the size is ROW+1

• INT * JA

8.10.1 Detailed Description

Block sparse row storage matrix of REAL type.

Note

This data structure is adapted from the Intel MKL library. Refer to: http://software.intel.-com/sites/products/documentation/hpc/mkl/lin/index.htm

Some of the following entries are capitalized to stress that they are for blocks!

Definition at line 37 of file fasp_block.h.

8.10.2 Field Documentation

8.10.2.1 INT* JA

Element i of the integer array columns is the number of the column in the block matrix that contains the i-th non-zero block. The size is NNZ.

Definition at line 67 of file fasp block.h.

8.10.2.2 **REAL*** val

A real array that contains the elements of the non-zero blocks of a sparse matrix. The elements are stored block-by-block in row major order. A non-zero block is the block that contains at least one non-zero element. All elements of non-zero blocks are stored, even if some of them is equal to zero. Within each nonzero block elements are stored in row-major order and the size is (NNZ*nb*nb).

Definition at line 60 of file fasp_block.h.

The documentation for this struct was generated from the following file:

· fasp_block.h

8.11 dCOOmat Struct Reference

Sparse matrix of REAL type in COO (or IJ) format.

```
#include <fasp.h>
```

Data Fields

INT row

row number of matrix A, m

INT col

column of matrix A, n

• INT nnz

number of nonzero entries

• INT * I

integer array of row indices, the size is nnz

• INT * J

integer array of column indices, the size is nnz

• REAL * val

nonzero entries of A

8.11.1 Detailed Description

Sparse matrix of REAL type in COO (or IJ) format.

Coordinate Format (I,J,A)

Note

The starting index of A is 0.

Definition at line 209 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

8.12 dCSRLmat Struct Reference

Sparse matrix of REAL type in CSRL format.

```
#include <fasp.h>
```

Data Fields

INT row

number of rows

INT col

number of cols

• INT nnz

number of nonzero entries

• INT dif

number of different values in i-th row, i=0:nrows-1

• INT * nz_diff

nz_diff[i]: the i-th different value in 'nzrow'

• INT * index

row index of the matrix (length-grouped): rows with same nnz are together

• INT * start

j in {start[i],...,start[i+1]-1} means nz_diff[i] nnz in index[j]-row

• INT * ja

column indices of all the nonzeros

• REAL * val

values of all the nonzero entries

8.12.1 Detailed Description

Sparse matrix of REAL type in CSRL format.

Definition at line 265 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

8.13 dCSRmat Struct Reference

Sparse matrix of REAL type in CSR format.

```
#include <fasp.h>
```

Data Fields

• INT row

row number of matrix A, m

INT col

column of matrix A, n

INT nnz

number of nonzero entries

• INT * IA

integer array of row pointers, the size is m+1

• INT * JA

integer array of column indexes, the size is nnz

REAL * val

nonzero entries of A

8.13.1 Detailed Description

Sparse matrix of REAL type in CSR format.

CSR Format (IA,JA,A) in REAL

Note

The starting index of A is 0.

Definition at line 149 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.14 ddenmat Struct Reference

Dense matrix of REAL type.

```
#include <fasp.h>
```

Data Fields

• INT row

number of rows

INT col

number of columns

• REAL ** val

actual matrix entries

8.14.1 Detailed Description

Dense matrix of REAL type.

A dense REAL matrix

Definition at line 109 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

8.15 dSTRmat Struct Reference

Structure matrix of REAL type.

```
#include <fasp.h>
```

Data Fields

• INT nx

number of grids in x direction

• INT ny

number of grids in y direction

INT nz

number of grids in z direction

INT nxy

number of grids on x-y plane

INT nc

size of each block (number of components)

INT ngrid

number of grids

• REAL * diag

diagonal entries (length is $ngrid*(nc^2)$)

INT nband

number of off-diag bands

INT * offsets

offsets of the off-diagals (length is nband)

REAL ** offdiag

off-diagonal entries (dimension is nband * [(ngrid-|offsets|) * $nc^{\wedge}2$])

8.15.1 Detailed Description

Structure matrix of REAL type.

Note

Every nc² entries of the array diag and off-diag[i] store one block: For 2D matrix, the recommended offsets is [-1,1,-nx,nx]; For 3D matrix, the recommended offsets is [-1,1,-nx,nx,-nxy,nxy].

Definition at line 304 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

8.16 dvector Struct Reference

Vector with n entries of REAL type.

```
#include <fasp.h>
```

Data Fields

INT row

number of rows

• REAL * val

actual vector entries

8.16.1 Detailed Description

Vector with n entries of REAL type.

Definition at line 342 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.17 grid2d Struct Reference

Two dimensional grid data structure.

```
#include <fasp.h>
```

Data Fields

- REAL(* p)[2]
- INT(* e)[2]
- INT(* t)[3]
- INT(* s)[3]
- INT * pdiri
- INT * ediri
- INT * pfather
- INT * efather
- INT * tfatherINT vertices
- INT edges
- INT triangles

8.17.1 Detailed Description

Two dimensional grid data structure.

Note

The grid2d structure is simply a list of triangles, edges and vertices. edge i has 2 vertices e[i], triangle i has 3 edges s[i], 3 vertices t[i] vertex i has two coordinates p[i]

Definition at line 1006 of file fasp.h.

8.17.2 Field Documentation

8.17.2.1 **INT**(* e)[2]

Vertices of edges

Definition at line 1009 of file fasp.h.

8.17.2.2 INT edges

Number of edges

Definition at line 1020 of file fasp.h.

8.17.2.3 INT* ediri

Boundary flags (0 <=> interior edge)

Definition at line 1013 of file fasp.h.

8.17.2.4 **INT*** efather

Father edge or triangle

Definition at line 1016 of file fasp.h.

8.17.2.5 **REAL**(* p)[2]

Coordinates of vertices

Definition at line 1008 of file fasp.h.

8.17.2.6 INT* pdiri

Boundary flags (0 <=> interior point)

Definition at line 1012 of file fasp.h.

8.17.2.7 **INT*** pfather

Father point or edge

Definition at line 1015 of file fasp.h.

8.17.2.8 **INT**(* s)[3]

Edges of triangles

Definition at line 1011 of file fasp.h.

8.17.2.9 INT(* t)[3]

Vertices of triangles

Definition at line 1010 of file fasp.h.

8.17.2.10 INT* tfather

Father triangle

Definition at line 1017 of file fasp.h.

8.17.2.11 **INT** triangles

Number of triangles

Definition at line 1021 of file fasp.h.

8.17.2.12 INT vertices

Number of grid points

Definition at line 1019 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

8.18 iCOOmat Struct Reference

Sparse matrix of INT type in COO (or IJ) format.

```
#include <fasp.h>
```

Data Fields

INT row

row number of matrix A, m

INT col

column of matrix A, n

• INT nnz

number of nonzero entries

• INT * I

integer array of row indices, the size is nnz

• INT * J

integer array of column indices, the size is nnz

INT * val

nonzero entries of A

8.18.1 Detailed Description

Sparse matrix of INT type in COO (or IJ) format.

Coordinate Format (I,J,A)

Note

The starting index of A is 0.

Definition at line 239 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.19 iCSRmat Struct Reference

Sparse matrix of INT type in CSR format.

```
#include <fasp.h>
```

Data Fields

INT row

row number of matrix A, m

INT col

column of matrix A, n

INT nnz

number of nonzero entries

• INT * IA

integer array of row pointers, the size is m+1

• INT * JA

integer array of column indexes, the size is nnz

• INT * val

nonzero entries of A

8.19.1 Detailed Description

Sparse matrix of INT type in CSR format.

CSR Format (IA,JA,A) in integer

Note

The starting index of A is 0.

Definition at line 179 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.20 idenmat Struct Reference

Dense matrix of INT type.

```
#include <fasp.h>
```

Data Fields

INT row

number of rows

INT col

number of columns

INT ** val

actual matrix entries

8.20.1 Detailed Description

Dense matrix of INT type.

A dense INT matrix

Definition at line 128 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

8.21 ILU_data Struct Reference

Data for ILU setup.

```
#include <fasp.h>
```

Data Fields

INT row

row number of matrix LU, m

• INT col

column of matrix LU, n

• INT nzlu

number of nonzero entries

• INT * ijlu

integer array of row pointers and column indexes, the size is nzlu

• REAL * luval

nonzero entries of LU

• INT nb

block size for BSR type only

• INT nwork

work space size

REAL * work

work space

8.21.1 Detailed Description

Data for ILU setup.

Definition at line 400 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.22 ILU_param Struct Reference

Parameters for ILU.

```
#include <fasp.h>
```

Data Fields

SHORT print_level

print leve

SHORT ILU_type

ILU type for decomposition.

• INT ILU Ifil

level of fill-in for ILUk

• REAL ILU_droptol

drop tolerence for ILUt

• REAL ILU_relax

add the sum of dropped elements to diagnal element in proportion relax

REAL ILU_permtol

```
permuted if permtol*|a(i,j)| > |a(i,i)|
```

8.22.1 Detailed Description

Parameters for ILU.

Definition at line 374 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

8.23 input_param Struct Reference

Input parameters.

```
#include <fasp.h>
```

Data Fields

- SHORT print_level
- SHORT output_type
- char workdir [256]
- INT problem_num
- SHORT solver_type
- SHORT precond_type
- SHORT stop_type
- · REAL itsolver tol
- · INT itsolver maxit
- INT restart
- SHORT ILU_type
- INT ILU Ifil
- · REAL ILU droptol
- REAL ILU relax
- REAL ILU permtol
- INT Schwarz_mmsize
- INT Schwarz maxlvl
- INT Schwarz_type
- SHORT AMG type
- SHORT AMG_levels
- SHORT AMG_cycle_type
- SHORT AMG_smoother
- SHORT AMG_smooth_order
- REAL AMG_relaxation
- SHORT AMG polynomial degree
- SHORT AMG_presmooth_iter
- SHORT AMG_postsmooth_iter
- INT AMG_coarse_dof
- REAL AMG_tol
- INT AMG maxit
- SHORT AMG_ILU_levels
- SHORT AMG_coarse_scaling
- SHORT AMG_amli_degree
- SHORT AMG_nl_amli_krylov_type
- INT AMG_schwarz_levels
- SHORT AMG_coarsening_type
- SHORT AMG_interpolation_type
- REAL AMG_strong_threshold
- REAL AMG_truncation_threshold
- REAL AMG_max_row_sum
- INT AMG_aggressive_level
- INT AMG_aggressive_path
- REAL AMG_strong_coupled
- INT AMG_max_aggregation
- REAL AMG_tentative_smooth
- SHORT AMG_smooth_filter

8.23.1 Detailed Description

Input parameters.

Input parameters, reading from disk file

Definition at line 914 of file fasp.h.

8.23.2 Field Documentation

8.23.2.1 INT AMG_aggressive_level

number of levels use aggressive coarsening

Definition at line 969 of file fasp.h.

8.23.2.2 INT AMG_aggressive_path

number of paths used to determine strongly coupled C-set

Definition at line 970 of file fasp.h.

8.23.2.3 SHORT AMG_amli_degree

degree of the polynomial used by AMLI cycle

Definition at line 959 of file fasp.h.

8.23.2.4 INT AMG_coarse_dof

minimal coarsest level dof

Definition at line 954 of file fasp.h.

8.23.2.5 SHORT AMG_coarse_scaling

switch of scaling of the coarse grid correction

Definition at line 958 of file fasp.h.

8.23.2.6 SHORT AMG_coarsening_type

coarsening type

Definition at line 964 of file fasp.h.

8.23.2.7 SHORT AMG_cycle_type

type of cycle

Definition at line 947 of file fasp.h.

8.23.2.8 SHORT AMG_ILU_levels

how many levels use ILU smoother

Definition at line 957 of file fasp.h.

8.23.2.9 SHORT AMG_interpolation_type

interpolation type

Definition at line 965 of file fasp.h.

8.23.2.10 SHORT AMG_levels

maximal number of levels

Definition at line 946 of file fasp.h.

8.23.2.11 INT AMG_max_aggregation

max size of each aggregate

Definition at line 974 of file fasp.h.

8.23.2.12 REAL AMG_max_row_sum

maximal row sum

Definition at line 968 of file fasp.h.

8.23.2.13 **INT AMG_maxit**

number of iterations for AMG used as preconditioner

Definition at line 956 of file fasp.h.

8.23.2.14 SHORT AMG_nl_amli_krylov_type

type of krylov method used by nonlinear AMLI cycle

Definition at line 960 of file fasp.h.

8.23.2.15 SHORT AMG_polynomial_degree

degree of the polynomial smoother

Definition at line 951 of file fasp.h.

8.23.2.16 SHORT AMG_postsmooth_iter

number of postsmoothing

Definition at line 953 of file fasp.h.

8.23.2.17 SHORT AMG_presmooth_iter

number of presmoothing

Definition at line 952 of file fasp.h.

8.23.2.18 **REAL AMG_relaxation**

over-relaxation parameter for SOR

Definition at line 950 of file fasp.h.

8.23.2.19 INT AMG_schwarz_levels

number of levels use schwarz smoother

Definition at line 961 of file fasp.h.

8.23.2.20 SHORT AMG_smooth_filter

use filterfor smoothing the tentative prolongation or not

Definition at line 976 of file fasp.h.

8.23.2.21 SHORT AMG_smooth_order

order for smoothers

Definition at line 949 of file fasp.h.

8.23.2.22 SHORT AMG_smoother

type of smoother

Definition at line 948 of file fasp.h.

8.23.2.23 REAL AMG_strong_coupled

strong coupled threshold for aggregate

Definition at line 973 of file fasp.h.

8.23.2.24 REAL AMG_strong_threshold

strong threshold for coarsening

Definition at line 966 of file fasp.h.

8.23.2.25 REAL AMG_tentative_smooth

relaxation factor for smoothing the tentative prolongation

Definition at line 975 of file fasp.h.

8.23.2.26 **REAL AMG_tol**

tolerance for AMG if used as preconditioner

Definition at line 955 of file fasp.h.

8.23.2.27 REAL AMG_truncation_threshold

truncation factor for interpolation

Definition at line 967 of file fasp.h.

8.23.2.28 SHORT AMG_type

Type of AMG

Definition at line 945 of file fasp.h.

8.23.2.29 REAL ILU_droptol

drop tolerance

Definition at line 935 of file fasp.h.

8.23.2.30 INT ILU_IfiI

level of fill-in

Definition at line 934 of file fasp.h.

8.23.2.31 REAL ILU_permtol

permutation tolerance

Definition at line 937 of file fasp.h.

8.23.2.32 REAL ILU_relax

scaling factor: add the sum of dropped entries to diagnal

Definition at line 936 of file fasp.h.

8.23.2.33 SHORT ILU_type

ILU type for decomposition

Definition at line 933 of file fasp.h.

8.23.2.34 INT itsolver_maxit

maximal number of iterations for iterative solvers

Definition at line 929 of file fasp.h.

8.23.2.35 REAL itsolver_tol

tolerance for iterative linear solver

Definition at line 928 of file fasp.h.

8.23.2.36 SHORT output_type

type of output stream

Definition at line 918 of file fasp.h.

8.23.2.37 SHORT precond_type

type of preconditioner for iterative solvers

Definition at line 926 of file fasp.h.

8.23.2.38 SHORT print_level

print level

Definition at line 917 of file fasp.h.

8.23.2.39 INT problem_num

problem number to solve

Definition at line 922 of file fasp.h.

8.23.2.40 INT restart

restart number used in GMRES

Definition at line 930 of file fasp.h.

8.23.2.41 INT Schwarz_maxlvl

maximal levels

Definition at line 941 of file fasp.h.

8.23.2.42 INT Schwarz_mmsize

maximal block size

Definition at line 940 of file fasp.h.

8.23.2.43 INT Schwarz_type

type of schwarz method

Definition at line 942 of file fasp.h.

8.23.2.44 SHORT solver_type

type of iterative solvers

Definition at line 925 of file fasp.h.

8.23.2.45 SHORT stop_type

type of stopping criteria for iterative solvers

Definition at line 927 of file fasp.h.

8.23.2.46 char workdir[256]

working directory for data files

Definition at line 921 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

8.24 itsolver_param Struct Reference

Parameters passed to iterative solvers.

#include <fasp.h>

Data Fields

- SHORT itsolver_type
- SHORT precond_type
- SHORT stop_type
- INT maxit
- · REAL tol
- INT restart
- SHORT print_level

8.24.1 Detailed Description

Parameters passed to iterative solvers.

Definition at line 984 of file fasp.h.

8.24.2 Field Documentation

8.24.2.1 SHORT itsolver_type

solver type: see message.h

Definition at line 986 of file fasp.h.

8.24.2.2 INT maxit

max number of iterations

Definition at line 989 of file fasp.h.

8.24.2.3 SHORT precond_type

preconditioner type: see message.h

Definition at line 987 of file fasp.h.

8.24.2.4 SHORT print_level

print level: 0-10

Definition at line 992 of file fasp.h.

8.24.2.5 INT restart

number of steps for restarting: for GMRES etc

Definition at line 991 of file fasp.h.

8.24.2.6 SHORT stop_type

stopping criteria type

Definition at line 988 of file fasp.h.

8.24.2.7 **REAL** tol

convergence tolerance

Definition at line 990 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

8.25 ivector Struct Reference

Vector with n entries of INT type.

#include <fasp.h>

Data Fields

• INT row

number of rows

• INT * val

actual vector entries

8.25.1 Detailed Description

Vector with n entries of INT type.

Definition at line 356 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

8.26 Link Struct Reference

Struct for Links.

```
#include <fasp.h>
```

Data Fields

INT prev

previous node in the linklist

INT next

next node in the linklist

8.26.1 Detailed Description

Struct for Links.

Definition at line 1033 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.27 linked_list Struct Reference

A linked list node.

```
#include <fasp.h>
```

Data Fields

• INT data

data

INT head

starting of the list

INT tail

ending of the list

• struct linked_list * next_node

next node

struct linked_list * prev_node

previous node

8.27.1 Detailed Description

A linked list node.

Note

This definition is adapted from hypre 2.0.

Definition at line 1050 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.28 mxv_matfree Struct Reference

Matrix-vector multiplication, replace the actual matrix.

```
#include <fasp.h>
```

Data Fields

```
    void * data
        data for MxV, can be a Matrix or something else
    void(* fct )(void *, REAL *, REAL *)
        action for MxV, void function pointer
```

8.28.1 Detailed Description

Matrix-vector multiplication, replace the actual matrix.

Definition at line 898 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.29 precond Struct Reference

Preconditioner data and action.

```
#include <fasp.h>
```

Data Fields

```
    void * data
        data for preconditioner, void pointer
    void(* fct )(REAL *, REAL *, void *)
        action for preconditioner, void function pointer
```

8.29.1 Detailed Description

Preconditioner data and action.

Note

This is the preconditioner structure for preconditioned iterative methods.

Definition at line 879 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.30 precond_block_data Struct Reference

Data passed to the preconditioner for block diagonal preconditioning.

```
#include <fasp_block.h>
```

Data Fields

- dCSRmat * A
- dvector * r
- dCSRmat ** Ablock
- ivector ** row idx
- ivector ** col_idx
- AMG_param * amgparam
- dCSRmat ** Aarray

8.30.1 Detailed Description

Data passed to the preconditioner for block diagonal preconditioning.

Note

This is needed for the diagnoal block preconditioner.

Definition at line 460 of file fasp_block.h.

8.30.2 Field Documentation

8.30.2.1 dCSRmat* A

problem data, the sparse matrix

Definition at line 462 of file fasp_block.h.

8.30.2.2 dCSRmat** Aarray

data generated in the setup phase

Definition at line 470 of file fasp block.h.

8.30.2.3 dCSRmat** Ablock

problem data, the blocks

Definition at line 465 of file fasp_block.h.

8.30.2.4 AMG_param * amgparam

parameters for AMG

Definition at line 469 of file fasp_block.h.

8.30.2.5 ivector** col_idx

problem data, col indices

Definition at line 467 of file fasp block.h.

8.30.2.6 dvector* r

problem data, the right-hand side vector

Definition at line 463 of file fasp_block.h.

8.30.2.7 ivector** row_idx

problem data, row indices

Definition at line 466 of file fasp_block.h.

The documentation for this struct was generated from the following file:

• fasp_block.h

8.31 precond_block_reservoir_data Struct Reference

Data passed to the preconditioner for preconditioning reservoir simulation problems.

#include <fasp_block.h>

Data Fields

• block_Reservoir * A

problem data in block_Reservoir format

block_dCSRmat * Abcsr

problem data in block_dCSRmat format

dCSRmat * Acsr

problem data in CSR format

INT ILU_Ifil

level of fill-in for structured ILU(k)

dSTRmat * LU

LU matrix for Reservoir-Reservoir block in STR format.

ILU data * LUcsr

LU matrix for Reservoir-Reservoir block in CSR format.

• AMG_data * mgl_data

AMG data for presure-presure block.

· SHORT print level

print level in AMG preconditioner

INT maxit AMG

max number of iterations of AMG preconditioner

SHORT max levels

max number of AMG levels

· REAL amg tol

tolerance for AMG preconditioner

SHORT cycle_type

AMG cycle type.

· SHORT smoother

AMG smoother type.

SHORT presmooth_iter

number of presmoothing

SHORT postsmooth_iter

number of postsmoothing

SHORT coarsening_type

coarsening type

REAL relaxation

relaxation parameter for SOR smoother

SHORT coarse_scaling

switch of scaling of coarse grid correction

INT maxit

max number of iterations

INT restart

number of iterations for restart

REAL tol

tolerance for convergence

• REAL * invS

inverse of the schur complement (-I - Awr*Arr $^{\setminus}$ {-1}*Arw) $^{\wedge}$ {-1}, Arr may be replaced by LU

dvector * DPSinvDSS

Diag(PS) * inv(Diag(SS))

- SHORT scaled
- · ivector * perf_idx
- dSTRmat * RR
- dCSRmat * WW
- dCSRmat * PP
- dSTRmat * SS
- precond_diagstr * diag
- dvector * diaginv
- ivector * pivot
- dvector * diaginvS
- ivector * pivotS
- · ivector * order
- · dvector r
- REAL * w

8.31.1 Detailed Description

Data passed to the preconditioner for preconditioning reservoir simulation problems.

Note

This is only needed for the Black Oil model with wells

Definition at line 361 of file fasp block.h.

8.31.2 Field Documentation

8.31.2.1 precond_diagstr* diag

the diagonal inverse for diagonal scaling

Definition at line 441 of file fasp_block.h.

8.31.2.2 dvector* diaginv

the inverse of the diagonals for GS/block GS smoother (whole reservoir matrix)

Definition at line 442 of file fasp_block.h.

8.31.2.3 dvector* diaginvS

the inverse of the diagonals for GS/block GS smoother (saturation block)

Definition at line 444 of file fasp_block.h.

8.31.2.4 ivector* order

order for smoothing

Definition at line 446 of file fasp_block.h.

8.31.2.5 ivector* perf_idx

variable index for perf

Definition at line 434 of file fasp_block.h.

8.31.2.6 ivector* pivot

the pivot for the GS/block GS smoother (whole reservoir matrix)

Definition at line 443 of file fasp_block.h.

8.31.2.7 ivector* pivotS

the pivot for the GS/block GS smoother (saturation block)

Definition at line 445 of file fasp block.h.

8.31.2.8 dCSRmat* PP

pressure block after diagonal scaling

Definition at line 438 of file fasp_block.h.

8.31.2.9 dvector r

temporary dvector used to store and restore the residual

Definition at line 449 of file fasp_block.h.

8.31.2.10 dSTRmat* RR

Diagonal scaled reservoir block

Definition at line 436 of file fasp_block.h.

8.31.2.11 SHORT scaled

whether the matirx is scaled

Definition at line 433 of file fasp block.h.

8.31.2.12 dSTRmat* SS

saturation block after diaogonal scaling

Definition at line 439 of file fasp_block.h.

8.31.2.13 **REAL*** w

temporary work space for other usage

Definition at line 450 of file fasp_block.h.

8.31.2.14 dCSRmat* WW

Argumented well block

Definition at line 437 of file fasp_block.h.

The documentation for this struct was generated from the following file:

fasp_block.h

8.32 precond_data Struct Reference

Data passed to the preconditioners.

#include <fasp.h>

Data Fields

SHORT AMG_type

type of AMG method

SHORT print level

print level in AMG preconditioner

INT maxit

max number of iterations of AMG preconditioner

SHORT max levels

max number of AMG levels

· REAL tol

tolerance for AMG preconditioner

SHORT cycle_type

AMG cycle type.

· SHORT smoother

AMG smoother type.

SHORT smooth_order

AMG smoother ordering.

· SHORT presmooth_iter

number of presmoothing

SHORT postsmooth_iter

number of postsmoothing

· REAL relaxation

coarsening type

SHORT polynomial_degree

degree of the polynomial smoother

• SHORT coarsening_type

switch of scaling of the coarse grid correction

SHORT coarse_scaling

relaxation parameter for SOR smoother

SHORT amli_degree

degree of the polynomial used by AMLI cycle

• SHORT nl_amli_krylov_type

type of krylov method used by Nonlinear AMLI cycle

· REAL tentative_smooth

smooth factor for smoothing the tentative prolongation

REAL * amli_coef

coefficients of the polynomial used by AMLI cycle

• AMG_data * mgl_data

AMG preconditioner data.

• ILU data * LU

ILU preconditioner data (needed for CPR type preconditioner)

dCSRmat * A

Matrix data.

· dvector r

temporary dvector used to store and restore the residual

• REAL * w

temporary work space for other usage

8.32.1 Detailed Description

Data passed to the preconditioners.

Definition at line 691 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.33 precond_data_bsr Struct Reference

Data passed to the preconditioners.

```
#include <fasp_block.h>
```

Data Fields

SHORT AMG_type

type of AMG method

SHORT print_level

print level in AMG preconditioner

INT maxit

max number of iterations of AMG preconditioner

INT max levels

max number of AMG levels

· REAL tol

tolerance for AMG preconditioner

SHORT cycle_type

AMG cycle type.

SHORT smoother

AMG smoother type.

SHORT smooth_order

AMG smoother ordering.

· SHORT presmooth_iter

number of presmoothing

SHORT postsmooth_iter

number of postsmoothing

SHORT coarsening_type

coarsening type

· REAL relaxation

relaxation parameter for SOR smoother

• SHORT coarse_scaling

switch of scaling of the coarse grid correction

SHORT amli_degree

degree of the polynomial used by AMLI cycle

REAL * amli_coef

coefficients of the polynomial used by AMLI cycle

· REAL tentative_smooth

smooth factor for smoothing the tentative prolongation

SHORT nl_amli_krylov_type

type of krylov method used by Nonlinear AMLI cycle

AMG data bsr * mgl data

AMG preconditioner data.

AMG_data * pres_mgl_data

AMG preconditioner data for pressure block.

ILU data * LU

ILU preconditioner data (needed for CPR type preconditioner)

dBSRmat * A

Matrix data.

dvector r

temporary dvector used to store and restore the residual

• REAL * w

temporary work space for other usage

8.33.1 Detailed Description

Data passed to the preconditioners.

Note

This structure is needed for the AMG solver/preconditioner in BSR format

Definition at line 282 of file fasp block.h.

The documentation for this struct was generated from the following file:

· fasp_block.h

8.34 precond_data_str Struct Reference

Data passed to the preconditioner for dSTRmat matrices.

```
#include <fasp.h>
```

Data Fields

SHORT AMG type

type of AMG method

SHORT print_level

print level in AMG preconditioner

INT maxit

max number of iterations of AMG preconditioner

SHORT max_levels

max number of AMG levels

REAL tol

tolerance for AMG preconditioner

SHORT cycle_type

AMG cycle type.

SHORT smoother

AMG smoother type.

· SHORT presmooth_iter

number of presmoothing

· SHORT postsmooth iter

number of postsmoothing

SHORT coarsening_type

coarsening type

· REAL relaxation

relaxation parameter for SOR smoother

· SHORT coarse_scaling

switch of scaling of the coarse grid correction

AMG_data * mgl_data

AMG preconditioner data.

• ILU_data * LU

ILU preconditioner data (needed for CPR type preconditioner)

SHORT scaled

whether the matrx are scaled or not

dCSRmat * A

the orginal CSR matrix

dSTRmat * A_str

stor the whole reservoir block in STR format

dSTRmat * SS_str

store Saturation block in STR format

dvector * diaginv

the inverse of the diagonals for GS/block GS smoother (whole reservoir matrix)

ivector * pivot

the pivot for the GS/block GS smoother (whole reservoir matrix)

dvector * diaginvS

the inverse of the diagonals for GS/block GS smoother (saturation block)

ivector * pivotS

the pivot for the GS/block GS smoother (saturation block)

· ivector * order

order for smoothing

ivector * neigh

arrary to store neighbor information

• dvector r

temporary dvector used to store and restore the residual

• REAL * w

temporary work space for other usage

8.34.1 Detailed Description

Data passed to the preconditioner for dSTRmat matrices.

Definition at line 770 of file fasp.h.

The documentation for this struct was generated from the following file:

• fasp.h

8.35 precond_diagbsr Struct Reference

Data passed to diagnal preconditioner for dBSRmat matrices.

```
#include <fasp_block.h>
```

Data Fields

• INT nb

dimension of each sub-block

· dvector diag

diagnal elements

8.35.1 Detailed Description

Data passed to diagnal preconditioner for dBSRmat matrices.

Note

This is needed for the diagnal preconditioner.

Definition at line 264 of file fasp_block.h.

The documentation for this struct was generated from the following file:

• fasp_block.h

8.36 precond_diagstr Struct Reference

Data passed to diagnal preconditioner for dSTRmat matrices.

```
#include <fasp.h>
```

Data Fields

• INT nc

number of components

· dvector diag

diagnal elements

8.36.1 Detailed Description

Data passed to diagnal preconditioner for dSTRmat matrices.

Note

This is needed for the diagnal preconditioner.

Definition at line 863 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.37 precond_FASP_blkoil_data Struct Reference

Data passed to the preconditioner for preconditioning reservoir simulation problems.

```
#include <fasp_block.h>
```

Data Fields

• block BSR * A

Part 1: Basic data.

SHORT scaled

Part 2: Data for CPR-like preconditioner for reservoir block.

- dvector * diaginv_noscale
- dBSRmat * RR
- ivector * neigh
- ivector * order
- dBSRmat * SS
- dvector * diaginv_S
- ivector * pivot_S
- dCSRmat * PP
- AMG_data * mgl_data
- SHORT print_level

print level in AMG preconditioner

INT maxit_AMG

max number of iterations of AMG preconditioner

SHORT max_levels

max number of AMG levels

REAL amg_tol

tolerance for AMG preconditioner

SHORT cycle_type

AMG cycle type.

· SHORT smoother

AMG smoother type.

SHORT smooth_order

AMG smoothing order.

· SHORT presmooth_iter

number of presmoothing

SHORT postsmooth_iter

number of postsmoothing

• SHORT coarsening_type

coarsening type

REAL relaxation

relaxation parameter for SOR smoother

SHORT coarse scaling

switch of scaling of coarse grid correction

SHORT amli_degree

degree of the polynomial used by AMLI cycle

• REAL * amli_coef

coefficients of the polynomial used by AMLI cycle

· REAL tentative_smooth

relaxation parameter for smoothing the tentative prolongation

- · dvector * diaginv
- ivector * pivot
- ILU data * LU

data of ILU for reservoir block

- ivector * perf_idx
- ivector * perf_neigh
- dCSRmat * WW
- void * Numeric

data for direct solver for argumented well block

• REAL * invS

inverse of the schur complement (-I - Awr*Arr^{-1}*Arw)^{-1}, Arr may be replaced by LU

- INT maxit
- INT restart
- REAL tol
- dvector r
- REAL * w

8.37.1 Detailed Description

Data passed to the preconditioner for preconditioning reservoir simulation problems.

Note

This is only needed for the Black Oil model with wells

Definition at line 480 of file fasp_block.h.

8.37.2 Field Documentation

8.37.2.1 block_BSR* A

Part 1: Basic data.

whole jacobian system in block_BSRmat

Definition at line 485 of file fasp block.h.

8.37.2.2 dvector* diaginv

inverse of the diagonal blocks of reservoir block

Definition at line 554 of file fasp_block.h.

8.37.2.3 dvector* diaginv_noscale

inverse of diagonal blocks for diagonal scaling

Definition at line 492 of file fasp_block.h.

8.37.2.4 dvector* diaginv_S

inverse of the diagonal blocks of saturation block

Definition at line 501 of file fasp_block.h.

8.37.2.5 INT maxit

max number of iterations

Definition at line 572 of file fasp_block.h.

8.37.2.6 AMG data* mgl_data

AMG data for presure-presure block

Definition at line 506 of file fasp_block.h.

8.37.2.7 ivector* neigh

neighbor information of the reservoir block

Definition at line 496 of file fasp_block.h.

8.37.2.8 ivector* order

ordering of the reservoir block

Definition at line 497 of file fasp_block.h.

8.37.2.9 ivector* perf_idx

index of blocks which have perforation

Definition at line 561 of file fasp_block.h.

8.37.2.10 ivector* perf_neigh

index of blocks which are neighbors of perforations (include perforations)

Definition at line 562 of file fasp_block.h.

8.37.2.11 ivector* pivot

pivot for the GS smoothers for the reservoir matrix

Definition at line 555 of file fasp_block.h.

8.37.2.12 ivector* pivot_S

pivoting for the GS smoothers for saturation block

Definition at line 502 of file fasp_block.h.

8.37.2.13 dCSRmat* PP

pressure block

Definition at line 505 of file fasp block.h.

8.37.2.14 dvector r

temporary dvector used to store and restore the residual

Definition at line 577 of file fasp_block.h.

8.37.2.15 INT restart

number of iterations for restart

Definition at line 573 of file fasp_block.h.

8.37.2.16 dBSRmat* RR

reservoir block

Definition at line 493 of file fasp block.h.

8.37.2.17 SHORT scaled

Part 2: Data for CPR-like preconditioner for reservoir block.

scaled = 1 means the the following RR block is diagonal scaled

Definition at line 491 of file fasp_block.h.

8.37.2.18 dBSRmat* SS

saturation block

Definition at line 500 of file fasp_block.h.

8.37.2.19 REAL tol

tolerance

Definition at line 574 of file fasp_block.h.

8.37.2.20 REAL* w

temporary work space for other usage

Definition at line 578 of file fasp_block.h.

8.37.2.21 dCSRmat* WW

Argumented well block

Definition at line 563 of file fasp_block.h.

The documentation for this struct was generated from the following file:

• fasp_block.h

8.38 Schwarz_data Struct Reference

Data for Schwarz methods.

#include <fasp.h>

Data Fields

dCSRmat A

pointer to the matrix

• INT nblk

number of blocks

• INT * iblock

row index of blocks

• INT * jblock

column index of blocks

REAL * rhsloc

local right hand side

• REAL * au

LU decomposition: the U block.

• REAL * al

LU decomposition: the L block.

• INT schwarz_type

Schwarz method type.

INT memt

working space size

INT * mask

mask

• INT * maxa

maxa

8.38.1 Detailed Description

Data for Schwarz methods.

This is needed for the schwarz solver, preconditioner/smoother.

Definition at line 459 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

8.39 Schwarz_param Struct Reference

Parameters for Schwarz method.

```
#include <fasp.h>
```

Data Fields

SHORT print_level

print leve

SHORT schwarz_type

type for Schwarz method

INT schwarz maxlvl

maximal level for constructing the blocks

• INT schwarz_mmsize

maxiaml size of blocks

8.39.1 Detailed Description

Parameters for Schwarz method.

Added on 05/14/2012

Definition at line 435 of file fasp.h.

The documentation for this struct was generated from the following file:

· fasp.h

Data	Structure	Docum	antation

Chapter 9

File Documentation

9.1 amg.c File Reference

AMG method as an iterative solver (main file)

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

• void fasp_solver_amg (dCSRmat *A, dvector *b, dvector *x, AMG_param *param)

Solve Ax = b by algebaric multigrid methods.

9.1.1 Detailed Description

AMG method as an iterative solver (main file)

Definition in file amg.c.

9.1.2 Function Documentation

```
9.1.2.1 void fasp_solver_amg ( dCSRmat * A, dvector * b, dvector * x, AMG_param * param )
```

Solve Ax = b by algebraic multigrid methods.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
Х	Pointer to dvector: the unknowns

66 File Documentation

param Pointer to AMG_param: AMG parameters

Author

Chensong Zhang

Date

04/06/2010

Note

Refer to "Multigrid" by U. Trottenberg, C. W. Oosterlee and A. Schuller Appendix A.7 (by A. Brandt, P. Oswald and K. Stuben) Academic Press Inc., San Diego, CA, 2001.

Modified by Chensong Zhang on 01/10/2012 Modified by Chensong Zhang on 05/05/2013: Remove error handling from AMG setup

Definition at line 37 of file amg.c.

9.2 amg_setup_aggregation_bsr.inl File Reference

Utilies for multigrid cycles in BSR format.

9.2.1 Detailed Description

Utilies for multigrid cycles in BSR format.

Definition in file amg_setup_aggregation_bsr.inl.

9.3 amg_setup_aggregation_csr.inl File Reference

Utilies for multigrid cycles for CSR matrices.

9.3.1 Detailed Description

Utilies for multigrid cycles for CSR matrices.

Definition in file amg_setup_aggregation_csr.inl.

9.4 amg_setup_cr.c File Reference

Brannick-Falgout compatible relaxation based AMG: SETUP phase.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

SHORT fasp_amg_setup_cr (AMG_data *mgl, AMG_param *param)
 Set up phase of Brannick Falgout CR coarsening for classic AMG.

9.4.1 Detailed Description

Brannick-Falgout compatible relaxation based AMG: SETUP phase.

Note

Setup A, P, R and levels using the Compatible Relaxation coarsening for classic AMG interpolation Refer to J. Brannick and R. Falgout "Compatible relaxation and coarsening in AMG"

TODO: Not working. Yet need to be fixed. -Chensong

Definition in file amg_setup_cr.c.

9.4.2 Function Documentation

```
9.4.2.1 SHORT fasp_amg_setup_cr ( AMG data * mgl, AMG param * param )
```

Set up phase of Brannick Falgout CR coarsening for classic AMG.

Parameters

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

Returns

SUCCESS if successed, otherwise, error information.

Author

James Brannick

Date

04/21/2010

Modified by Chensong Zhang on 05/10/2013: adjust the structure.

Definition at line 38 of file amg_setup_cr.c.

9.5 amg_setup_rs.c File Reference

Ruge-Stuben AMG: SETUP phase.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

68 File Documentation

Functions

• INT fasp_amg_setup_rs (AMG_data *mgl, AMG_param *param)

Setup phase of Ruge and Stuben's classic AMG.

INT fasp amg setup rs omp (AMG data *mgl, AMG param *param)

Setup of AMG based on R-S coarsening.

9.5.1 Detailed Description

Ruge-Stuben AMG: SETUP phase.

Note

Setup A, P, R, levels using classic AMG! Refter to "Multigrid" by Stuben in U. Trottenberg, C. W. Oosterlee and A. Schuller. Appendix A.7 (by A. Brandt, P. Oswald and K. Stuben). Academic Press Inc., San Diego, CA, 2001.

Definition in file amg_setup_rs.c.

9.5.2 Function Documentation

9.5.2.1 INT fasp_amg_setup_rs (AMG_data * mgl, AMG_param * param)

Setup phase of Ruge and Stuben's classic AMG.

Parameters

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

Returns

SUCCESS if successed, otherwise, error information.

Author

Chensong Zhang

Date

05/09/2010

Modified by Chensong Zhang on 04/04/2009. Modified by Chensong Zhang on 05/09/2010. Modified by Zhiyang Zhou on 11/17/2010. Modified by Xiaozhe Hu on 01/23/2011: add AMLI cycle. Modified by Chensong zhang on 09/09/2011: add min dof. Modified by Xiaozhe Hu on 04/24/2013: aggressive coarsening. Modified by Chensong Zhang on 05/03/2013: add error handling in setup. Modified by Chensong Zhang on 05/10/2013: adjust the structure.

Definition at line 47 of file amg_setup_rs.c.

9.5.2.2 INT fasp_amg_setup_rs_omp (AMG_data * mgl, AMG_param * param)

Setup of AMG based on R-S coarsening.

Parameters

mgl	Pointer to AMG_data data
param	Pointer to AMG parameters

Returns

SUCCESS if successed, otherwise, error information.

Author

Chunsheng Feng, Xiaoqiang Yue

Date

03/11/2011

Definition at line 253 of file amg_setup_rs.c.

9.6 amg_setup_sa.c File Reference

Smoothed aggregation AMG: SETUP phase.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "amg_setup_aggregation_csr.inl"
```

Functions

SHORT fasp_amg_setup_sa (AMG_data *mgl, AMG_param *param)
 Set up phase of smoothed aggregation AMG.

9.6.1 Detailed Description

Smoothed aggregation AMG: SETUP phase.

Note

Setup A, P, PT and levels using the unsmoothed aggregation algorithm; Refer to P. Vanek, J. Madel and M. Brezina "Algebraic Multigrid on Unstructured Meshes", 1994

Definition in file amg_setup_sa.c.

9.6.2 Function Documentation

```
9.6.2.1 SHORT fasp_amg_setup_sa ( AMG_data * mgl, AMG_param * param )
```

Set up phase of smoothed aggregation AMG.

70 File Documentation

Parameters

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

Returns

SUCCESS if succeed, error otherwise

Author

Xiaozhe Hu

Date

09/29/2009

Note

Only for testing smoothed P and unsmoothed A, not used usually.

Modified by Chensong Zhang on 04/06/2010. Modified by Chensong Zhang on 05/09/2010. Modified by Xiaozhe Hu on 01/23/2011: add AMLI cycle Modified by Chensong Zhang on 05/10/2013: adjust the structure.

Definition at line 50 of file amg setup sa.c.

9.7 amg_setup_ua.c File Reference

Unsmoothed aggregation AMG: SETUP phase.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "amg_setup_aggregation_csr.inl"
#include "amg_setup_aggregation_bsr.inl"
```

Functions

- SHORT fasp amg setup ua (AMG data *mgl, AMG param *param)
 - Set up phase of unsmoothed aggregation AMG.
- SHORT fasp_amg_setup_ua_bsr (AMG_data_bsr *mgl, AMG_param *param)

Set up phase of unsmoothed aggregation AMG (BSR format)

9.7.1 Detailed Description

Unsmoothed aggregation AMG: SETUP phase.

Note

Setup A, P, PT and levels using the unsmoothed aggregation algorithm; Refer to P. Vanek, J. Madel and M. Brezina "Algebraic Multigrid on Unstructured Meshes", 1994

Definition in file amg setup ua.c.

9.7.2 Function Documentation

```
9.7.2.1 SHORT fasp_amg_setup_ua ( AMG_data * mgl, AMG_param * param )
```

Set up phase of unsmoothed aggregation AMG.

Parameters

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

Returns

SUCCESS if succeed, error otherwise

Author

Xiaozhe Hu

Date

12/28/2011

Definition at line 39 of file amg_setup_ua.c.

```
9.7.2.2 INT fasp_amg_setup_ua_bsr ( AMG_data_bsr * mgl, AMG_param * param )
```

Set up phase of unsmoothed aggregation AMG (BSR format)

Parameters

mgl	Pointer to AMG data: AMG_data_bsr
param	Pointer to AMG parameters: AMG_param

Returns

SUCCESS if succeed, error otherwise

Author

Xiaozhe Hu

Date

03/16/2012

Definition at line 70 of file amg_setup_ua.c.

9.8 amg_solve.c File Reference

Algebraic multigrid iterations: SOLVE phase.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

72 File Documentation

Functions

```
• INT fasp_amg_solve (AMG_data *mgl, AMG_param *param)
```

AMG - SOLVE phase.

• INT fasp_amg_solve_amli (AMG_data *mgl, AMG_param *param)

AMLI - SOLVE phase.

INT fasp amg solve nl amli (AMG data *mgl, AMG param *param)

Nonlinear AMLI — SOLVE phase.

void fasp_famg_solve (AMG_data *mgl, AMG_param *param)

FMG - SOLVE phase.

9.8.1 Detailed Description

Algebraic multigrid iterations: SOLVE phase.

Note

Solve Ax=b using multigrid method. This is SOLVE phase only and is independent of SETUP method used! Should be called after multigrid hierarchy has been generated!

Definition in file amg_solve.c.

9.8.2 Function Documentation

9.8.2.1 INT fasp_amg_solve (AMG_data * mgl, AMG_param * param)

AMG - SOLVE phase.

Parameters

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

Returns

Iteration number if succeed, ERROR otherwise

Author

Xuehai Huang, Chensong Zhang

Date

04/02/2010

Modified by Chensong 04/21/2013: Fix an output typo

Definition at line 36 of file amg_solve.c.

9.8.2.2 INT fasp_amg_solve_amli (AMG_data * mgl, AMG_param * param)

AMLI - SOLVE phase.

m	Pointer to AMG data: AMG_data	
para	Pointer to AMG parameters: AMG_param	

Returns

Iteration number if succeed, ERROR otherwise

Author

Xiaozhe Hu

Date

01/23/2011

Modified by Chensong 04/21/2013: Fix an output typo

Definition at line 119 of file amg_solve.c.

9.8.2.3 INT fasp_amg_solve_nl_amli (AMG_data * mgl, AMG_param * param)

Nonlinear AMLI — SOLVE phase.

Parameters

	mgl	Pointer to AMG data: AMG_data
ĺ	param	Pointer to AMG parameters: AMG_param

Returns

Iteration number if succeed, ERROR otherwise

Author

Xiaozhe Hu

Date

04/30/2011

Modified by Chensong 04/21/2013: Fix an output typo

Definition at line 198 of file amg_solve.c.

9.8.2.4 void fasp_famg_solve ($AMG_data * mgl, AMG_param * param$)

FMG - SOLVE phase.

Parameters

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

Author

Chensong Zhang

Date

01/10/2012

Definition at line 270 of file amg_solve.c.

9.9 amlirecur.c File Reference

Abstract AMLI multilevel iteration - recursive version.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "forts_ns.h"
#include "mg_util.inl"
```

Functions

- void fasp_solver_amli (AMG_data *mgl, AMG_param *param, INT level)

 Solve Ax=b with recursive AMLI-cycle.
- void fasp_solver_nl_amli (AMG_data *mgl, AMG_param *param, INT level, INT num_levels) Solve Ax=b with recursive nonlinear AMLI-cycle.
- void fasp_solver_nl_amli_bsr (AMG_data_bsr *mgl, AMG_param *param, INT level, INT num_levels)

 Solve Ax=b with recursive nonlinear AMLI-cycle.
- void fasp_amg_amli_coef (const REAL lambda_max, const REAL lambda_min, const INT degree, REAL *coef)
 Compute the coefficients of the polynomial used by AMLI-cycle.

9.9.1 Detailed Description

Abstract AMLI multilevel iteration – recursive version.

Note

Contains AMLI and nonlinear AMLI cycles

TODO: Need to add a non-recursive version! -Chensong

Definition in file amlirecur.c.

- 9.9.2 Function Documentation
- 9.9.2.1 void fasp_amg_amli_coef (const REAL lambda_max, const REAL lambda_min, const INT degree, REAL * coef)

Compute the coefficients of the polynomial used by AMLI-cycle.

Parameters

	lambda_max	Maximal lambda
	lambda_min	Minimal lambda
	degree	Degree of polynomial approximation
Ī	coef	Coefficient of AMLI (output)

Author

Xiaozhe Hu

Date

01/23/2011

Definition at line 743 of file amlirecur.c.

9.9.2.2 void fasp_solver_amli (AMG_data * mgl, AMG_param * param, INT level)

Solve Ax=b with recursive AMLI-cycle.

Parameters

m	gl Po	ointer to AMG data: AMG_data
para	m Po	ointer to AMG parameters: AMG_param
lev	rel Cu	urrent level

Author

Xiaozhe Hu

Date

01/23/2011

Modified by Chensong Zhang on 02/27/2013: update direct solvers.

Definition at line 37 of file amlirecur.c.

9.9.2.3 void fasp_solver_nl_amli (AMG_data * mgl, AMG_param * param, INT level, INT num_levels)

Solve Ax=b with recursive nonlinear AMLI-cycle.

Parameters

mgl	Pointer to AMG_data data
param	Pointer to AMG parameters
level	Current level
num_levels	Total numebr of levels

Author

Xiaozhe Hu

Date

04/06/2010

Modified by Chensong Zhang on 02/27/2013: update direct solvers.

Definition at line 292 of file amlirecur.c.

9.9.2.4 void fasp_solver_nl_amli_bsr (AMG_data_bsr * mgl, AMG_param * param, INT level, INT num_levels)

Solve Ax=b with recursive nonlinear AMLI-cycle.

Parameters

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param
level	Current level
num_levels	Total numebr of levels

Author

Xiaozhe Hu

Date

04/06/2010

Modified by Chensong Zhang on 02/27/2013: update direct solvers.

Definition at line 565 of file amlirecur.c.

9.10 array.c File Reference

Array operations.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void fasp_array_null (REAL *x)

Initialize an array.

void fasp_array_set (const INT n, REAL *x, const REAL val)

Set initial value for an array to be x=val.

void fasp_iarray_set (const INT n, INT *x, const INT val)

Set initial value for an array to be x=val.

void fasp_array_cp (const INT n, REAL *x, REAL *y)

Copy an array to the other y=x.

void fasp_iarray_cp (const INT n, INT *x, INT *y)

Copy an array to the other y=x.

```
• void fasp_array_cp_nc3 (REAL *x, REAL *y)
```

Copy an array to the other y=x, the length is 3.

void fasp_array_cp_nc5 (REAL *x, REAL *y)

Copy an array to the other y=x, the length is 5.

void fasp_array_cp_nc7 (REAL *x, REAL *y)

Copy an array to the other y=x, the length is 7.

9.10.1 Detailed Description

Array operations. Simple array operations - init, set, copy, etc

Definition in file array.c.

9.10.2 Function Documentation

```
9.10.2.1 void fasp_array_cp ( const INT n, REAL * x, REAL * y )
```

Copy an array to the other y=x.

Parameters

n	Number of variables
X	Pointer to the original vector
У	Pointer to the destination vector

Author

Chensong Zhang

Date

2010/04/03

Definition at line 172 of file array.c.

9.10.2.2 void fasp_array_cp_nc3 (REAL * x, REAL * y)

Copy an array to the other y=x, the length is 3.

Parameters

X	Pointer to the original vector
у	Pointer to the destination vector

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Note

Special unrolled routine designed for a specific application

Definition at line 212 of file array.c.

```
9.10.2.3 void fasp_array_cp_nc5 ( REAL * x, REAL * y )
```

Copy an array to the other y=x, the length is 5.

Parameters

X	Pointer to the original vector
У	Pointer to the destination vector

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Note

Special unrolled routine designed for a specific application

Definition at line 233 of file array.c.

```
9.10.2.4 void fasp_array_cp_nc7 ( REAL * x, REAL * y )
```

Copy an array to the other y=x, the length is 7.

Parameters

X	Pointer to the original vector
у	Pointer to the destination vector

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Note

Special unrolled routine designed for a specific application

Definition at line 256 of file array.c.

9.10.2.5 void fasp_array_null (REAL * x)

Initialize an array.

Parameters

X	Pointer to the vector

Author

Chensong Zhang

Date

2010/04/03

Definition at line 32 of file array.c.

9.10.2.6 void fasp_array_set (const INT n, REAL * x, const REAL val)

Set initial value for an array to be x=val.

Parameters

n	Number of variables
X	Pointer to the vector
val	Initial value for the REAL array

Author

Chensong Zhang

Date

04/03/2010

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 52 of file array.c.

9.10.2.7 void fasp_iarray_cp (const INT n, INT * x, INT * y)

Copy an array to the other y=x.

Parameters

n	Number of variables
Х	Pointer to the original vector
у	Pointer to the destination vector

Author

Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 192 of file array.c.

```
9.10.2.8 void fasp_iarray_set ( const INT n, INT * x, const INT val )
```

Set initial value for an array to be x=val.

Parameters

n	Number of variables
Х	Pointer to the vector
val	Initial value for the REAL array

Author

Chensong Zhang

Date

04/03/2010

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/25/2012

Definition at line 114 of file array.c.

9.11 blas_array.c File Reference

BLAS operations for arrays.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

```
    void fasp_blas_array_ax (const INT n, const REAL a, REAL *x)
```

```
x = a * x
```

void fasp_blas_array_axpy (const INT n, const REAL a, REAL *x, REAL *y)

```
y = a * x + y
```

void fasp_blas_array_axpyz (const INT n, const REAL a, REAL *x, REAL *y, REAL *z)

```
z = a * x + v
```

• void fasp_blas_array_axpby (const INT n, const REAL a, REAL *x, const REAL b, REAL *y)

```
y = a * x + b * y
```

REAL fasp_blas_array_dotprod (const INT n, REAL *x, REAL *y)
 Inner product of two arraies (x,y)

• REAL fasp_blas_array_norm1 (const INT n, REAL *x)

L1 norm of array x.

REAL fasp_blas_array_norm2 (const INT n, REAL *x)

L2 norm of array x.

• REAL fasp_blas_array_norminf (const INT n, REAL *x)

Linf norm of array x.

9.11.1 Detailed Description

BLAS operations for arrays.

Definition in file blas_array.c.

9.11.2 Function Documentation

9.11.2.1 void fasp_blas_array_ax (const INT n, const REAL a, REAL *x)

x = a * x

Parameters

n	Number of variables
а	Factor a
X	Pointer to x

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Note

x is reused to store the resulting array.

Definition at line 35 of file blas_array.c.

9.11.2.2 void fasp_blas_array_axpby (const INT n, const REAL * x, const REAL * y)

y = a*x + b*y

n	Number of variables
а	Factor a
X	Pointer to x
b	Factor b
у	Pointer to y

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Note

y is reused to store the resulting array.

Definition at line 218 of file blas_array.c.

9.11.2.3 void fasp_blas_array_axpy (const INT n, const REAL a, REAL * x, REAL * y)

y = a*x + y

Parameters

n	Number of variables
а	Factor a
X	Pointer to x
у	Pointer to y

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Note

y is reused to store the resulting array.

Definition at line 87 of file blas_array.c.

9.11.2.4 void fasp_blas_array_axpyz (const INT n, const REAL a, REAL * x, REAL * y, REAL * z)

z = a*x + y

Parameters

n	Number of variables
а	Factor a
X	Pointer to x
у	Pointer to y
Z	Pointer to z

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 167 of file blas_array.c.

9.11.2.5 REAL fasp_blas_array_dotprod (const INT n, REAL * x, REAL * y)

Inner product of two arraies (x,y)

Parameters

n	Number of variables
X	Pointer to x
у	Pointer to y

Returns

Inner product (x,y)

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 267 of file blas_array.c.

9.11.2.6 REAL fasp_blas_array_norm1 (const INT n, REAL * x)

L1 norm of array x.

n	Number of variables
X	Pointer to x

Returns

L1 norm of x

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 308 of file blas_array.c.

9.11.2.7 REAL fasp_blas_array_norm2 (const INT n, REAL *x)

L2 norm of array x.

Parameters

	n	Number of variables
ĺ	X	Pointer to x

Returns

L2 norm of x

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 348 of file blas_array.c.

9.11.2.8 REAL fasp_blas_array_norminf (const INT n, REAL * x)

Linf norm of array x.

Parameters

n	Number of variables
X	Pointer to x

Returns

L_inf norm of x

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Zheng Li on 06/28/2012

Definition at line 388 of file blas_array.c.

9.12 blas bcsr.c File Reference

BLAS operations for block_dCSRmat matrices.

```
#include <time.h>
#include "fasp.h"
#include "fasp_block.h"
#include "fasp_functs.h"
```

Functions

```
    void fasp_blas_bdcsr_aAxpy (const REAL alpha, block_dCSRmat *A, REAL *x, REAL *y)
```

Matrix-vector multiplication y = alpha*A*x + y.

void fasp_blas_bdcsr_mxv (block_dCSRmat *A, REAL *x, REAL *y)

Matrix-vector multiplication y = A*x.

void fasp_blas_bdbsr_aAxpy (const REAL alpha, block_BSR *A, REAL *x, REAL *y)

Matrix-vector multiplication y = alpha*A*x + y.

void fasp_blas_bdbsr_mxv (block_BSR *A, REAL *x, REAL *y)

Matrix-vector multiplication y = A*x.

9.12.1 Detailed Description

BLAS operations for block_dCSRmat matrices.

Definition in file blas bcsr.c.

9.12.2 Function Documentation

9.12.2.1 void fasp_blas_bdbsr_aAxpy (const REAL alpha, block_BSR * A, REAL * x, REAL * y)

Matrix-vector multiplication y = alpha*A*x + y.

Parameters

alpha	REAL factor a
Α	Pointer to block_BSR matrix A
X	Pointer to array x
У	Pointer to array y

Author

Xiaozhe Hu

Date

11/11/2010

Definition at line 231 of file blas_bcsr.c.

9.12.2.2 void fasp_blas_bdbsr_mxv (block_BSR * A, REAL * x, REAL * y)

Matrix-vector multiplication y = A*x.

Parameters

Α	Pointer to block_BSR matrix A
X	Pointer to array x
у	Pointer to array y

Author

Xiaozhe Hu

Date

11/11/2010

Definition at line 269 of file blas_bcsr.c.

9.12.2.3 void fasp_blas_bdcsr_aAxpy (const REAL alpha, block_dCSRmat * A, REAL * X, REAL * Y)

Matrix-vector multiplication y = alpha*A*x + y.

Parameters

alpha	REAL factor a
Α	Pointer to block_dCSRmat matrix A
X	Pointer to array x
у	Pointer to array y

Author

Xiaozhe Hu

Date

06/04/2010

Definition at line 30 of file blas_bcsr.c.

```
9.12.2.4 void fasp_blas_bdcsr_mxv ( block_dCSRmat * A, REAL * x, REAL * y )
```

Matrix-vector multiplication y = A*x.

Parameters

Α	Pointer to block_dCSRmat matrix A
X	Pointer to array x
у	Pointer to array y

Author

Chensong Zhang

Date

04/27/2013

Definition at line 130 of file blas bcsr.c.

9.13 blas bsr.c File Reference

BLAS operations for dBSRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

- void fasp_blas_dbsr_aAxpby (const REAL alpha, dBSRmat *A, REAL *x, const REAL beta, REAL *y)
 Compute y := alpha*A*x + beta*y.
- void fasp_blas_dbsr_aAxpy (const REAL alpha, dBSRmat *A, REAL *x, REAL *y)
 Compute y := alpha*A*x + y.
- void fasp_blas_dbsr_mxv (dBSRmat *A, REAL *x, REAL *y)
 Compute y := A*x.
- void fasp_blas_dbsr_rap1 (dBSRmat *R, dBSRmat *A, dBSRmat *P, dBSRmat *B)
 dBSRmat sparse matrix multiplication B=R*A*P
- void fasp_blas_dbsr_rap (dBSRmat *R, dBSRmat *A, dBSRmat *P, dBSRmat *B)
 dBSRmat sparse matrix multiplication B=R*A*P

9.13.1 Detailed Description

BLAS operations for dBSRmat matrices.

Definition in file blas bsr.c.

9.13.2 Function Documentation

9.13.2.1 void fasp_blas_dbsr_aAxpby (const REAL alpha, dBSRmat * A, REAL * x, const REAL beta, REAL * y)

Compute y := alpha*A*x + beta*y.

alpha	REAL factor alpha
Α	Pointer to the dBSRmat matrix
X	Pointer to the array x
beta	REAL factor beta
У	Pointer to the array y

Author

Zhiyang Zhou

Date

10/25/2010

Modified by Chunsheng Feng, Zheng Li

Date

06/29/2012

Note

Works for general nb (Xiaozhe)

Definition at line 39 of file blas_bsr.c.

9.13.2.2 void fasp_blas_dbsr_aAxpy (const REAL alpha, dBSRmat * A, REAL * x, REAL * y)

Compute y := alpha*A*x + y.

Parameters

alpha	REAL factor alpha
Α	Pointer to the dBSRmat matrix
X	Pointer to the array x
У	Pointer to the array y

Author

Zhiyang Zhou

Date

10/25/2010

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Note

Works for general nb (Xiaozhe)

Definition at line 320 of file blas_bsr.c.

9.13.2.3 void fasp_blas_dbsr_mxv (dBSRmat * A, REAL * x, REAL * y)

Compute y := A*x.

Α	Pointer to the dBSRmat matrix
X	Pointer to the array x
У	Pointer to the array y

Author

Zhiyang Zhou

Date

10/25/2010

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Note

Works for general nb (Xiaozhe)

Definition at line 595 of file blas_bsr.c.

9.13.2.4 void fasp_blas_dbsr_rap (dBSRmat * R, dBSRmat * A, dBSRmat * P, dBSRmat * B)

dBSRmat sparse matrix multiplication B=R*A*P

Parameters

R	Pointer to the dBSRmat matrix
Α	Pointer to the dBSRmat matrix
Р	Pointer to the dBSRmat matrix
В	Pointer to dBSRmat matrix equal to R*A*P (output)

Author

Chunsheng Feng, Zheng Li

Date

10/24/2012

Note

Ref. R.E. Bank and C.C. Douglas. SMMP: Sparse Matrix Multiplication Package. Advances in Computational Mathematics, 1 (1993), pp. 127-137.

Definition at line 2528 of file blas_bsr.c.

9.13.2.5 void fasp_blas_dbsr_rap1 (dBSRmat*R, dBSRmat*A, dBSRmat*P, dBSRmat*B)

dBSRmat sparse matrix multiplication B=R*A*P

Parameters

R	Pointer to the dBSRmat matrix
Α	Pointer to the dBSRmat matrix
Р	Pointer to the dBSRmat matrix
В	Pointer to dBSRmat matrix equal to R*A*P (output)

Author

Chunsheng Feng, Xiaoqiang Yue and Xiaozhe Hu

Date

08/08/2011

Note

Ref. R.E. Bank and C.C. Douglas. SMMP: Sparse Matrix Multiplication Package. Advances in Computational Mathematics, 1 (1993), pp. 127-137.

Definition at line 2344 of file blas_bsr.c.

9.14 blas csr.c File Reference

BLAS operations for dCSRmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

- INT fasp_blas_dcsr_add (dCSRmat *A, const REAL alpha, dCSRmat *B, const REAL beta, dCSRmat *C)
 compute C = alpha*A + beta*B in CSR format
- void fasp_blas_dcsr_axm (dCSRmat *A, const REAL alpha)

Multiply a sparse matrix A in CSR format by a scalar alpha.

void fasp_blas_dcsr_mxv (dCSRmat *A, REAL *x, REAL *y)

Matrix-vector multiplication y = A*x.

void fasp_blas_dcsr_mxv_agg (dCSRmat *A, REAL *x, REAL *y)

Matrix-vector multiplication y = A*x, where the entries of A are all ones.

void fasp_blas_dcsr_aAxpy (const REAL alpha, dCSRmat *A, REAL *x, REAL *y)

Matrix-vector multiplication y = alpha*A*x + y.

void fasp_blas_dcsr_aAxpy_agg (const REAL alpha, dCSRmat *A, REAL *x, REAL *y)

Matrix-vector multiplication y = alpha*A*x + y, where the entries of A are all ones.

REAL fasp_blas_dcsr_vmv (dCSRmat *A, REAL *x, REAL *y)

vector-Matrix-vector multiplication alpha = y'*A*x

void fasp blas dcsr mxm (dCSRmat *A, dCSRmat *B, dCSRmat *C)

Sparse matrix multiplication C=A*B.

• void fasp_blas_dcsr_rap (dCSRmat *R, dCSRmat *A, dCSRmat *P, dCSRmat *RAP)

Triple sparse matrix multiplication B=R*A*P.

void fasp_blas_dcsr_rap_agg (dCSRmat *R, dCSRmat *A, dCSRmat *P, dCSRmat *RAP)

Triple sparse matrix multiplication B=R*A*P.

void fasp_blas_dcsr_rap_agg1 (dCSRmat *R, dCSRmat *A, dCSRmat *P, dCSRmat *B)

Triple sparse matrix multiplication B=R*A*P, where the entries of R and P are all ones.

void fasp_blas_dcsr_ptap (dCSRmat *Pt, dCSRmat *A, dCSRmat *P, dCSRmat *Ac)

Triple sparse matrix multiplication B=P'*A*P.

void fasp blas dcsr rap4 (dCSRmat *R, dCSRmat *A, dCSRmat *P, dCSRmat *B, INT *icor ysk)

Triple sparse matrix multiplication B=R*A*P.

9.14.1 Detailed Description

BLAS operations for dCSRmat matrices.

Note

Sparse functions usually contain three runs. The three runs are all the same but thy serve different purpose.

Example: If you do c=a+b:

- first do a dry run to find the number of non-zeroes in the result and form ic;
- allocate space (memory) for jc and form this one;
- if you only care about a "boolean" result of the addition, you stop here;
- you call another routine, which uses ic and jc to perform the addition.

Definition in file blas csr.c.

9.14.2 Function Documentation

9.14.2.1 void fasp_blas_dcsr_aAxpy (const REAL alpha, dCSRmat * A, REAL * x, REAL * y)

Matrix-vector multiplication y = alpha*A*x + y.

Parameters

alpha	REAL factor alpha
Α	Pointer to dCSRmat matrix A
X	Pointer to array x
У	Pointer to array y

Author

Chensong Zhang

Date

07/01/2009

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/26/2012

Definition at line 480 of file blas csr.c.

9.14.2.2 void fasp_blas_dcsr_aAxpy_agg (const REAL alpha, dCSRmat * A, REAL * x, REAL * y)

Matrix-vector multiplication y = alpha*A*x + y, where the entries of A are all ones.

Parameters

alpha	REAL factor alpha
Α	Pointer to dCSRmat matrix A
Χ	Pointer to array x
у	Pointer to array y

Author

Xiaozhe Hu

Date

02/22/2011

Modified by Chunsheng Feng, Zheng Li on 08/29/2012

Definition at line 594 of file blas_csr.c.

9.14.2.3 void fasp_blas_dcsr_add (dCSRmat * A, const REAL alpha, dCSRmat * B, const REAL beta, dCSRmat * C)

compute C = alpha*A + beta*B in CSR format

Parameters

Α	Pointer to dCSRmat matrix
alpha	REAL factor alpha
В	Pointer to dCSRmat matrix
beta	REAL factor beta
С	Pointer to dCSRmat matrix

Returns

SUCCESS if succees, RUN_FAIL if not

Author

Xiaozhe Hu

Date

11/07/2009

Modified by Chunsheng Feng, Zheng Li on 06/29/2012

Definition at line 48 of file blas_csr.c.

9.14.2.4 void fasp_blas_dcsr_axm (dCSRmat * A, const REAL alpha)

Multiply a sparse matrix A in CSR format by a scalar alpha.

Α	Pointer to dCSRmat matrix A
alpha	REAL factor alpha

Author

Chensong Zhang

Date

07/01/2009

Modified by Chunsheng Feng, Zheng Li on 06/29/2012

Definition at line 201 of file blas_csr.c.

9.14.2.5 void fasp_blas_dcsr_mxm (dCSRmat * A, dCSRmat * B, dCSRmat * C)

Sparse matrix multiplication C=A*B.

Parameters

Α	Pointer to the dCSRmat matrix A
В	Pointer to the dCSRmat matrix B
С	Pointer to dCSRmat matrix equal to A*B

Author

Xiaozhe Hu

Date

11/07/2009

Note

This fct will be replaced! -Chensong

Definition at line 760 of file blas_csr.c.

9.14.2.6 void fasp_blas_dcsr_mxv (dCSRmat * A, REAL * x, REAL * y)

Matrix-vector multiplication y = A*x.

Parameters

Α	Pointer to dCSRmat matrix A
X	Pointer to array x

У	Pointer to array y
,	, ,

Author

Chensong Zhang

Date

07/01/2009

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/26/2012

Definition at line 225 of file blas_csr.c.

9.14.2.7 void fasp_blas_dcsr_mxv_agg (dCSRmat * A, REAL * X, REAL * Y)

Matrix-vector multiplication y = A*x, where the entries of A are all ones.

Parameters

Α	Pointer to dCSRmat matrix A
X	Pointer to array x
у	Pointer to array y

Author

Xiaozhe Hu

Date

02/22/2011

Modified by Chunsheng Feng, Zheng Li on 08/29/2012

Definition at line 423 of file blas_csr.c.

9.14.2.8 void fasp_blas_dcsr_ptap (dCSRmat * Pt, dCSRmat * A, dCSRmat * P, dCSRmat * Ac)

Triple sparse matrix multiplication B=P'*A*P.

Parameters

Pt	Pointer to the restriction matrix
Α	Pointer to the fine coefficient matrix
Р	Pointer to the prolongation matrix
Ac	Pointer to the coarse coefficient matrix (output)

Author

Ludmil Zikatanov, Chensong Zhang

Date

05/10/2010

Modified by Chunsheng Feng, Zheng Li on 10/19/2012

Note

Driver to compute triple matrix product P'*A*P using Itz CSR format. In Itx format: ia[0]=1, ja[0] and a[0] are used as usual. When called from Fortran, ia[0], ja[0] and a[0] will be just ia(1),ja(1),a(1). For the indices, $ia_t[tz[k] = ia_usual[k]+1$, $ja_t[tz[k] = ja_usual[k]+1$, $ja_t[tz[k] = ja_usual[k]+1]$, $ja_t[tz[k] = ja_t[tz[k]+1]+1]$

Definition at line 1598 of file blas_csr.c.

9.14.2.9 void fasp_blas_dcsr_rap (dCSRmat * R, dCSRmat * A, dCSRmat * P, dCSRmat * RAP)

Triple sparse matrix multiplication B=R*A*P.

Parameters

R	Pointer to the dCSRmat matrix R
Α	Pointer to the dCSRmat matrix A
Р	Pointer to the dCSRmat matrix P
RAP	Pointer to dCSRmat matrix equal to R*A*P

Author

Xuehai Huang, Chensong Zhang

Date

05/10/2010

Modified by Chunsheng Feng, Xiaogiang Yue on 05/26/2012

Note

Ref. R.E. Bank and C.C. Douglas. SMMP: Sparse Matrix Multiplication Package. Advances in Computational Mathematics, 1 (1993), pp. 127-137.

Definition at line 867 of file blas csr.c.

9.14.2.10 void fasp_blas_dcsr_rap4 (dCSRmat * R, dCSRmat * A, dCSRmat * P, dCSRmat * B, INT * icor_ysk)

Triple sparse matrix multiplication B=R*A*P.

Parameters

R	pointer to the dCSRmat matrix
Α	pointer to the dCSRmat matrix

Р	pointer to the dCSRmat matrix
В	pointer to dCSRmat matrix equal to R*A*P
icor_ysk	pointer to the array

Author

Feng Chunsheng, Yue Xiaoqiang

Date

08/02/2011

Note

Ref. R.E. Bank and C.C. Douglas. SMMP: Sparse Matrix Multiplication Package. Advances in Computational Mathematics, 1 (1993), pp. 127-137.

Definition at line 1697 of file blas_csr.c.

9.14.2.11 void fasp_blas_dcsr_rap_agg (dCSRmat * R, dCSRmat * A, dCSRmat * P, dCSRmat * RAP)

Triple sparse matrix multiplication B=R*A*P.

Parameters

R	Pointer to the dCSRmat matrix R
Α	Pointer to the dCSRmat matrix A
Р	Pointer to the dCSRmat matrix P
RAP	Pointer to dCSRmat matrix equal to R*A*P

Author

Xuehai Huang, Chensong Zhang

Date

05/10/2010

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/26/2012

Note

Ref. R.E. Bank and C.C. Douglas. SMMP: Sparse Matrix Multiplication Package. Advances in Computational Mathematics, 1 (1993), pp. 127-137.

Definition at line 1148 of file blas_csr.c.

9.14.2.12 void fasp_blas_dcsr_rap_agg1 (dCSRmat * R, dCSRmat * A, dCSRmat * P, dCSRmat * B)

Triple sparse matrix multiplication B=R*A*P, where the entries of R and P are all ones.

R	Pointer to the dCSRmat matrix R
Α	Pointer to the dCSRmat matrix A
Р	Pointer to the dCSRmat matrix P
В	Pointer to dCSRmat matrix equal to R*A*P

Author

Xiaozhe Hu

Date

02/21/2011

Note

Ref. R.E. Bank and C.C. Douglas. SMMP: Sparse Matrix Multiplication Package. Advances in Computational Mathematics, 1 (1993), pp. 127-137.

Definition at line 1415 of file blas_csr.c.

```
9.14.2.13 REAL fasp_blas_dcsr_vmv ( dCSRmat * A, REAL * x, REAL * y )
```

vector-Matrix-vector multiplication alpha = y'*A*x

Parameters

Α	Pointer to dCSRmat matrix A
X	Pointer to array x
У	Pointer to array y

Author

Chensong Zhang

Date

07/01/2009

Definition at line 705 of file blas_csr.c.

9.15 blas_csrl.c File Reference

BLAS operations for dCSRLmat matrices.

```
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void fasp_blas_dcsrl_mxv (dCSRLmat *A, REAL *x, REAL *y)
 Compute y = A*x for a sparse matrix in CSRL format.

9.15.1 Detailed Description

BLAS operations for dCSRLmat matrices.

Note

For details of CSRL format, refer to "Optimizaing sparse matrix vector product computations using unroll and jam" by John Mellor-Crummey and John Garvin, Tech Report Rice Univ, Aug 2002.

Definition in file blas csrl.c.

9.15.2 Function Documentation

```
9.15.2.1 void fasp_blas_dcsrl_mxv ( dCSRLmat * A, REAL * x, REAL * y )
```

Compute y = A*x for a sparse matrix in CSRL format.

Parameters

Α	Pointer to dCSRLmat matrix A
X	Pointer to REAL array of vector x
у	Pointer to REAL array of vector y

Date

2011/01/07

Definition at line 28 of file blas csrl.c.

9.16 blas smat.c File Reference

BLAS operations for small full matrix.

```
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

- void fasp_blas_smat_mxv_nc2 (REAL *a, REAL *b, REAL *c)
 - Compute the product of a 2*2 matrix a and a array b, stored in c.
- void fasp_blas_smat_mxv_nc3 (REAL *a, REAL *b, REAL *c)
 - Compute the product of a 3*3 matrix a and a array b, stored in c.
- void fasp_blas_smat_mxv_nc5 (REAL *a, REAL *b, REAL *c)
 - Compute the product of a 5*5 matrix a and a array b, stored in c.
- void fasp_blas_smat_mxv_nc7 (REAL *a, REAL *b, REAL *c)
 - Compute the product of a 7*7 matrix a and a array b, stored in c.
- void fasp_blas_smat_mxv (REAL *a, REAL *b, REAL *c, const INT n)
 - Compute the product of a small full matrix a and a array b, stored in c.
- void fasp blas smat mul nc2 (REAL *a, REAL *b, REAL *c)

```
Compute the matrix product of two 2* matrices a and b, stored in c.

    void fasp_blas_smat_mul_nc3 (REAL *a, REAL *b, REAL *c)

      Compute the matrix product of two 3*3 matrices a and b, stored in c.

    void fasp blas smat mul nc5 (REAL *a, REAL *b, REAL *c)

      Compute the matrix product of two 5*5 matrices a and b, stored in c.

    void fasp_blas_smat_mul_nc7 (REAL *a, REAL *b, REAL *c)

      Compute the matrix product of two 7*7 matrices a and b, stored in c.

    void fasp blas smat mul (REAL *a, REAL *b, REAL *c, const INT n)

      Compute the matrix product of two small full matrices a and b, stored in c.

    void fasp_blas_array_axpyz_nc2 (REAL a, REAL *x, REAL *y, REAL *z)

      z = a * x + v

    void fasp_blas_array_axpyz_nc3 (const REAL a, REAL *x, REAL *y, REAL *z)

      z = a * x + y

    void fasp_blas_array_axpyz_nc5 (const REAL a, REAL *x, REAL *y, REAL *z)

      z = a * x + v

    void fasp_blas_array_axpyz_nc7 (const REAL a, REAL *x, REAL *y, REAL *z)

      z = a * x + y

    void fasp_blas_array_axpy_nc2 (const REAL a, REAL *x, REAL *y)

      y = a*x + y, the length of x and y is 2

    void fasp_blas_array_axpy_nc3 (const REAL a, REAL *x, REAL *y)

      y = a*x + y, the length of x and y is 3

    void fasp_blas_array_axpy_nc5 (const REAL a, REAL *x, REAL *y)

      y = a*x + y, the length of x and y is 5

    void fasp_blas_array_axpy_nc7 (const REAL a, REAL *x, REAL *y)

      y = a*x + y, the length of x and y is 7

    void fasp_blas_smat_ypAx_nc2 (REAL *A, REAL *x, REAL *y)

      Compute y := y + Ax, where 'A' is a 2*2 dense matrix.

    void fasp_blas_smat_ypAx_nc3 (REAL *A, REAL *x, REAL *y)

      Compute y := y + Ax, where 'A' is a 3*3 dense matrix.

    void fasp_blas_smat_ypAx_nc5 (REAL *A, REAL *x, REAL *y)

      Compute y := y + Ax, where 'A' is a 5*5 dense matrix.

    void fasp_blas_smat_ypAx_nc7 (REAL *A, REAL *x, REAL *y)

      Compute y := y + Ax, where 'A' is a 7*7 dense matrix.

    void fasp blas smat ypAx (REAL *A, REAL *x, REAL *y, const INT n)

      Compute y := y + Ax, where 'A' is a n*n dense matrix.

    void fasp blas smat ymAx nc2 (REAL *A, REAL *x, REAL *y)

      Compute y := y - Ax, where 'A' is a n*n dense matrix.

    void fasp blas smat ymAx nc3 (REAL *A, REAL *x, REAL *y)

      Compute y := y - Ax, where 'A' is a n*n dense matrix.

    void fasp_blas_smat_ymAx_nc5 (REAL *A, REAL *x, REAL *y)

      Compute y := y - Ax, where 'A' is a n*n dense matrix.

    void fasp blas smat ymAx nc7 (REAL *A, REAL *x, REAL *y)

      Compute y := y - Ax, where 'A' is a 7*7 dense matrix.

    void fasp_blas_smat_ymAx (REAL *A, REAL *x, REAL *y, INT n)

      Compute y := y - Ax, where 'A' is a n*n dense matrix.

    void fasp blas smat aAxpby (const REAL alpha, REAL *A, REAL *x, const REAL beta, REAL *y, const INT n)

      Compute y:=alpha*A*x + beta*y.
```

void fasp_blas_smat_ymAx_ns2 (REAL *A, REAL *x, REAL *y)

Compute ys := ys - Ass*xs, where 'A' is a 2*2 dense matrix, Ass is its saturaton part 1*1.

void fasp_blas_smat_ymAx_ns3 (REAL *A, REAL *x, REAL *y)

Compute ys := ys - Ass*xs, where 'A' is a 3*3 dense matrix, Ass is its saturaton part 2*2.

void fasp_blas_smat_ymAx_ns5 (REAL *A, REAL *x, REAL *y)

Compute ys := ys - Ass*xs, where 'A' is a 5*5 dense matrix, Ass is its saturaton part 4*4.

void fasp_blas_smat_ymAx_ns7 (REAL *A, REAL *x, REAL *y)

Compute ys := ys - Ass*xs, where 'A' is a 7*7 dense matrix, Ass is its saturaton part 6*6.

void fasp blas smat ymAx ns (REAL *A, REAL *x, REAL *y, const INT n)

Compute ys := ys - Ass*xs, where 'A' is a n*n dense matrix, Ass is its saturaton part (n-1)*(n-1).

9.16.1 Detailed Description

BLAS operations for small full matrix.

Definition in file blas smat.c.

9.16.2 Function Documentation

9.16.2.1 void fasp_blas_array_axpy_nc2 (const REAL a, REAL * x, REAL * y)

y = a*x + y, the length of x and y is 2

Parameters

а	REAL factor a
Х	Pointer to the original array
у	Pointer to the destination array

Author

Xiaozhe Hu

Date

18/11/2011

Definition at line 627 of file blas_smat.c.

9.16.2.2 void fasp_blas_array_axpy_nc3 (const REAL a, REAL * x, REAL * y)

y = a*x + y, the length of x and y is 3

Parameters

а	REAL factor a
Х	Pointer to the original array

у	Pointer to the destination array

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 650 of file blas_smat.c.

9.16.2.3 void fasp_blas_array_axpy_nc5 (const REAL a, REAL * x, REAL * y)

y = a*x + y, the length of x and y is 5

Parameters

а	REAL factor a
X	Pointer to the original array
у	Pointer to the destination array

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 679 of file blas_smat.c.

9.16.2.4 void fasp_blas_array_axpy_nc7 (const REAL a, REAL * x, REAL * y)

y = a*x + y, the length of x and y is 7

Parameters

а	REAL factor a
Χ	Pointer to the original array
у	Pointer to the destination array

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 726 of file blas_smat.c.

9.16.2.5 void fasp_blas_array_axpyz_nc2 (REAL a, REAL * x, REAL * y, REAL * z)

z = a*x + y

Parameters

а	REAL factor a
X	Pointer to the original array 1
у	Pointer to the original array 2
Z	Pointer to the destination array

Author

Xiaozhe Hu

Date

18/11/2011

Note

z is the third array and the length of x, y and z is 2

Definition at line 442 of file blas_smat.c.

9.16.2.6 void fasp_blas_array_axpyz_nc3 (const REAL a, REAL * x, REAL * y, REAL * z)

z = a*x + y

Parameters

а	REAL factor a
X	Pointer to the original array 1
у	Pointer to the original array 2
Z	Pointer to the destination array

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Note

z is the third array and the length of x, y and z is 3

Definition at line 469 of file blas_smat.c.

9.16.2.7 void fasp_blas_array_axpyz_nc5 (const REAL a, REAL * x, REAL * y, REAL * z)

z = a*x + y

а	REAL factor a
X	Pointer to the original array 1
у	Pointer to the original array 2
Z	Pointer to the destination array

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Note

z is the third array and the length of x, y and z is 5

Definition at line 502 of file blas_smat.c.

9.16.2.8 void fasp_blas_array_axpyz_nc7 (const REAL a, REAL * x, REAL * y, REAL * z)

z = a*x + y

Parameters

а	REAL factor a
X	Pointer to the original array 1
У	Pointer to the original array 2
Z	Pointer to the destination array

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Note

z is the third array and the length of x, y and z is 7

Definition at line 553 of file blas_smat.c.

9.16.2.9 void fasp_blas_smat_aAxpby (const REAL alpha, REAL * A, REAL * x, const REAL beta, REAL * y, const INT n)

Compute y:=alpha*A*x + beta*y.

Parameters

alpha	REAL factor alpha
Α	Pointer to the REAL array which stands for a n∗n full matrix
X	Pointer to the REAL array with length n
beta	REAL factor beta
у	Pointer to the REAL array with length n
n	Length of array x and y

Author

Zhiyang Zhou

Date

2010/10/25

Definition at line 1250 of file blas_smat.c.

9.16.2.10 void fasp_blas_smat_mul (REAL * a, REAL * b, REAL * c, const INT n)

Compute the matrix product of two small full matrices a and b, stored in c.

Parameters

а	Pointer to the REAL array which stands a n∗n matrix
b	Pointer to the REAL array which stands a n∗n matrix
С	Pointer to the REAL array which stands a n∗n matrix
n	Dimension of the matrix

Author

Xiaozhe Hu, Shiquan Zhang

Date

04/21/2010

Definition at line 390 of file blas_smat.c.

9.16.2.11 void fasp_blas_smat_mul_nc2 (REAL * a, REAL * b, REAL * c)

Compute the matrix product of two 2* matrices a and b, stored in c.

Parameters

а	Pointer to the REAL array which stands a n*n matrix
b	Pointer to the REAL array which stands a n*n matrix
С	Pointer to the REAL array which stands a n*n matrix

Author

Xiaozhe Hu

Date

18/11/2011

Definition at line 175 of file blas_smat.c.

9.16.2.12 void fasp_blas_smat_mul_nc3 (REAL * a, REAL * b, REAL * c)

Compute the matrix product of two 3*3 matrices a and b, stored in c.

Parameters

а	Pointer to the REAL array which stands a n*n matrix
b	Pointer to the REAL array which stands a n*n matrix
С	Pointer to the REAL array which stands a n*n matrix

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 204 of file blas_smat.c.

9.16.2.13 void fasp_blas_smat_mul_nc5 (REAL * a, REAL * b, REAL * c)

Compute the matrix product of two 5*5 matrices a and b, stored in c.

Parameters

а	Pointer to the REAL array which stands a 5*5 matrix
b	Pointer to the REAL array which stands a 5∗5 matrix
С	Pointer to the REAL array which stands a 5*5 matrix

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 241 of file blas_smat.c.

9.16.2.14 void fasp_blas_smat_mul_nc7 (REAL * a, REAL * b, REAL * c)

Compute the matrix product of two 7*7 matrices a and b, stored in c.

Parameters

а	Pointer to the REAL array which stands a 7*7 matrix
b	Pointer to the REAL array which stands a 7*7 matrix
С	Pointer to the REAL array which stands a 7*7 matrix

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 300 of file blas_smat.c.

9.16.2.15 void fasp_blas_smat_mxv (REAL * a, REAL * b, REAL * c, const INT n)

Compute the product of a small full matrix a and a array b, stored in c.

Parameters

а	Pointer to the REAL array which stands a n∗n matrix
b	Pointer to the REAL array with length n
С	Pointer to the REAL array with length n
n	Dimension of the matrix

Author

Xiaozhe Hu, Shiquan Zhang

Date

04/21/2010

Definition at line 125 of file blas_smat.c.

9.16.2.16 void fasp_blas_smat_mxv_nc2 (REAL * a, REAL * b, REAL * c)

Compute the product of a 2*2 matrix a and a array b, stored in c.

Parameters

а	Pointer to the REAL array which stands a 2*2 matrix
b	Pointer to the REAL array with length 2
С	Pointer to the REAL array with length 2

Author

Xiaozhe Hu

Date

18/11/2010

Definition at line 25 of file blas_smat.c.

9.16.2.17 void fasp_blas_smat_mxv_nc3 (REAL * a, REAL * b, REAL * c)

Compute the product of a 3*3 matrix a and a array b, stored in c.

Parameters

а	Pointer to the REAL array which stands a 3*3 matrix
b	Pointer to the REAL array with length 3
С	Pointer to the REAL array with length 3

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 47 of file blas_smat.c.

9.16.2.18 void fasp_blas_smat_mxv_nc5 (REAL * a, REAL * b, REAL * c)

Compute the product of a 5*5 matrix a and a array b, stored in c.

Parameters

а	Pointer to the REAL array which stands a 5*5 matrix
b	Pointer to the REAL array with length 5
С	Pointer to the REAL array with length 5

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 70 of file blas_smat.c.

9.16.2.19 void fasp_blas_smat_mxv_nc7 (REAL * a, REAL * b, REAL * c)

Compute the product of a 7*7 matrix a and a array b, stored in c.

Parameters

а	Pointer to the REAL array which stands a 7*7 matrix
b	Pointer to the REAL array with length 7
С	Pointer to the REAL array with length 7

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 96 of file blas_smat.c.

9.16.2.20 void fasp_blas_smat_ymAx (REAL * A, REAL * X, REAL * Y, INT n)

Compute y := y - Ax, where 'A' is a n*n dense matrix.

Parameters

Α	Pointer to the n*n dense matrix
X	Pointer to the REAL array with length n
у	Pointer to the REAL array with length n
n	the dimension of the dense matrix

Author

Zhiyang Zhou, Xiaozhe Hu

Date

2010/10/25

Definition at line 1149 of file blas_smat.c.

9.16.2.21 void fasp_blas_smat_ymAx_nc2 (REAL * A, REAL * X, REAL * Y)

Compute y := y - Ax, where 'A' is a n*n dense matrix.

Parameters

Α	Pointer to the 2*2 dense matrix
X	Pointer to the REAL array with length 3
У	Pointer to the REAL array with length 3

Author

Xiaozhe Hu

Date

18/11/2011

Note

Works for 2-component

Definition at line 1019 of file blas_smat.c.

9.16.2.22 void fasp_blas_smat_ymAx_nc3 (REAL * A, REAL * X, REAL * Y)

Compute y := y - Ax, where 'A' is a n*n dense matrix.

Α	Pointer to the 3*3 dense matrix
Χ	Pointer to the REAL array with length 3

y Pointer to the REAL array with length 3

Author

Xiaozhe Hu, Zhiyang Zhou

Date

01/06/2011

Note

Works for 3-component

Definition at line 1047 of file blas_smat.c.

9.16.2.23 void fasp_blas_smat_ymAx_nc5 (REAL * A, REAL * X, REAL * Y)

Compute y := y - Ax, where 'A' is a n*n dense matrix.

Parameters

Ī	Α	Pointer to the 5*5 dense matrix
Ī	Χ	Pointer to the REAL array with length 5
Ī	У	Pointer to the REAL array with length 5

Author

Xiaozhe Hu, Zhiyang Zhou

Date

01/06/2011

Note

Works for 5-component

Definition at line 1077 of file blas_smat.c.

9.16.2.24 void fasp_blas_smat_ymAx_nc7 (REAL * A, REAL * X, REAL * Y)

Compute y := y - Ax, where 'A' is a 7*7 dense matrix.

Α	Pointer to the 7*7 dense matrix
Х	Pointer to the REAL array with length 7

y Pointer to the REAL array with length 7

Author

Xiaozhe Hu, Zhiyang Zhou

Date

01/06/2011

Note

Works for 7-component

Definition at line 1111 of file blas_smat.c.

9.16.2.25 void fasp_blas_smat_ymAx_ns (REAL * A, REAL * X, REAL * Y, const INT X)

Compute ys := ys - Ass*xs, where 'A' is a n*n dense matrix, Ass is its saturation part (n-1)*(n-1).

Parameters

Α	Pointer to the n*n dense matrix
X	Pointer to the REAL array with length n-1
у	Pointer to the REAL array with length n-1
n	the dimension of the dense matrix

Author

Xiaozhe Hu

Date

2010/10/25

Note

Only for block smoother for saturation block without explictly use saturation block!!

Definition at line 1424 of file blas_smat.c.

9.16.2.26 void fasp_blas_smat_ymAx_ns2 (REAL * A, REAL * X, REAL * Y)

Compute ys := ys - Ass*xs, where 'A' is a 2*2 dense matrix, Ass is its saturaton part 1*1.

Α	Pointer to the 2*2 dense matrix
---	---------------------------------

X	Pointer to the REAL array with length 1
у	Pointer to the REAL array with length 1

Author

Xiaozhe Hu

Date

2011/11/18

Note

Works for 2-component (Xiaozhe) Only for block smoother for saturation block without explicitly use saturation block!!

Definition at line 1300 of file blas_smat.c.

9.16.2.27 void fasp_blas_smat_ymAx_ns3 (REAL * A, REAL * X, REAL * Y)

Compute ys := ys - Ass*xs, where 'A' is a 3*3 dense matrix, Ass is its saturation part 2*2.

Parameters

Α	Pointer to the 3*3 dense matrix
Х	Pointer to the REAL array with length 2
у	Pointer to the REAL array with length 2

Author

Xiaozhe Hu

Date

2010/10/25

Note

Works for 3-component (Xiaozhe) Only for block smoother for saturation block without explictly use saturation block!!

Definition at line 1324 of file blas smat.c.

9.16.2.28 void fasp_blas_smat_ymAx_ns5 (REAL * A, REAL * X, REAL * Y)

Compute ys := ys - Ass*xs, where 'A' is a 5*5 dense matrix, Ass is its saturaton part 4*4.

Α	Pointer to the 5*5 dense matrix
X	Pointer to the REAL array with length 4
У	Pointer to the REAL array with length 4

Author

Xiaozhe Hu

Date

2010/10/25

Note

Works for 5-component (Xiaozhe) Only for block smoother for saturation block without explictly use saturation block!!

Definition at line 1352 of file blas_smat.c.

9.16.2.29 void fasp_blas_smat_ymAx_ns7 (REAL * A, REAL * X, REAL * Y)

Compute ys := ys - Ass*xs, where 'A' is a 7*7 dense matrix, Ass is its saturaton part 6*6.

Parameters

Α	Pointer to the 7*7 dense matrix
X	Pointer to the REAL array with length 6
у	Pointer to the REAL array with length 6

Author

Xiaozhe Hu

Date

2010/10/25

Note

Works for 7-component (Xiaozhe) Only for block smoother for saturation block without explicitly use saturation block!!

Definition at line 1386 of file blas_smat.c.

9.16.2.30 void fasp_blas_smat_ypAx (REAL * A, REAL * X, REAL * Y, const INT n)

Compute y := y + Ax, where 'A' is a n*n dense matrix.

Parameters

Α	Pointer to the n∗n dense matrix
X	Pointer to the REAL array with length n
у	Pointer to the REAL array with length n
n	Dimension of the dense matrix

Author

Zhiyang Zhou

Date

2010/10/25

Definition at line 918 of file blas_smat.c.

9.16.2.31 void fasp_blas_smat_ypAx_nc2 (REAL * A, REAL * X, REAL * Y)

Compute y := y + Ax, where 'A' is a 2*2 dense matrix.

Parameters

Α	Pointer to the 3*3 dense matrix
X	Pointer to the REAL array with length 3
У	Pointer to the REAL array with length 3

Author

Xiaozhe Hu

Date

2011/11/18

Definition at line 799 of file blas_smat.c.

9.16.2.32 void fasp_blas_smat_ypAx_nc3 (REAL * A, REAL * X, REAL * Y)

Compute y := y + Ax, where 'A' is a 3*3 dense matrix.

Parameters

Α	Pointer to the 3*3 dense matrix
Χ	Pointer to the REAL array with length 3
у	Pointer to the REAL array with length 3

Author

Zhiyang Zhou, Xiaozhe Hu

Date

2010/10/25

Definition at line 825 of file blas_smat.c.

9.16.2.33 void fasp_blas_smat_ypAx_nc5 (REAL * A, REAL * X, REAL * Y)

Compute y := y + Ax, where 'A' is a 5*5 dense matrix.

Parameters

Α	Pointer to the 5*5 dense matrix
X	Pointer to the REAL array with length 5
у	Pointer to the REAL array with length 5

Author

Zhiyang Zhou, Xiaozhe Hu

Date

2010/10/25

Definition at line 852 of file blas_smat.c.

```
9.16.2.34 void fasp_blas_smat_ypAx_nc7 ( REAL * A, REAL * X, REAL * Y )
```

Compute y := y + Ax, where 'A' is a 7*7 dense matrix.

Parameters

Α	Pointer to the 7*7 dense matrix
X	Pointer to the REAL array with length 7
у	Pointer to the REAL array with length 7

Author

Zhiyang Zhou, Xiaozhe Hu

Date

2010/10/25

Definition at line 883 of file blas_smat.c.

9.17 blas_str.c File Reference

BLAS operations for dSTRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

```
\bullet \ \ void \ fasp\_blas\_dstr\_aAxpy \ (REAL \ alpha, \ dSTRmat \ *A, \ REAL \ *x, \ REAL \ *y)\\
```

Matrix-vector multiplication y = alpha*A*x + y.

void fasp_blas_dstr_mxv (dSTRmat *A, REAL *x, REAL *y)

Matrix-vector multiplication y = A*x.

INT fasp_dstr_diagscale (dSTRmat *A, dSTRmat *B)
 B=D^{-1}A.

9.17.1 Detailed Description

BLAS operations for dSTRmat matrices.

Definition in file blas_str.c.

9.17.2 Function Documentation

9.17.2.1 void fasp_blas_dstr_aAxpy (REAL alpha, dSTRmat * A, REAL * x, REAL * y)

Matrix-vector multiplication y = alpha*A*x + y.

Parameters

alpha	REAL factor alpha
Α	Pointer to dSTRmat matrix
X	Pointer to REAL array
У	Pointer to REAL array

Author

Zhiyang Zhou, Xiaozhe Hu, Shiquan Zhang

Date

2010/10/15

Definition at line 47 of file blas_str.c.

9.17.2.2 void fasp_blas_dstr_mxv (dSTRmat * A, REAL * x, REAL * y)

Matrix-vector multiplication y = A*x.

Parameters

Α	Pointer to dSTRmat matrix
Х	Pointer to REAL array
У	Pointer to REAL array

Author

Chensong Zhang

Date

04/27/2013

Definition at line 117 of file blas_str.c.

9.17.2.3 INT fasp_dstr_diagscale (dSTRmat * A, dSTRmat * B)

 $B=D^{\setminus}\{-1\}A$.

Parameters

Α	Pointer to a 'dSTRmat' type matrix A
В	Pointer to a 'dSTRmat' type matrix B

Author

Shiquan Zhang

Date

2010/10/15

Modified by Chunsheng Feng, Zheng Li

Date

08/30/2012

Definition at line 142 of file blas_str.c.

9.18 blas_vec.c File Reference

BLAS operations for vectors.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

```
    void fasp_blas_dvec_axpy (const REAL a, dvector *x, dvector *y)
```

```
y = a * x + y
```

void fasp_blas_dvec_axpyz (const REAL a, dvector *x, dvector *y, dvector *z)

z = a*x + y, z is a third vector (z is cleared)

REAL fasp_blas_dvec_dotprod (dvector *x, dvector *y)

Inner product of two vectors (x,y)

REAL fasp_blas_dvec_relerr (dvector *x, dvector *y)

Relative error of two dvector x and y.

REAL fasp_blas_dvec_norm1 (dvector *x)

L1 norm of dvector x.

REAL fasp_blas_dvec_norm2 (dvector *x)

L2 norm of dvector x.

REAL fasp_blas_dvec_norminf (dvector *x)

Linf norm of dvector x.

9.18.1 Detailed Description

BLAS operations for vectors.

Definition in file blas_vec.c.

9.18.2 Function Documentation

9.18.2.1 void fasp_blas_dvec_axpy (const REAL a, dvector * x, dvector * y)

y = a*x + y

Parameters

а	REAL factor a
X	Pointer to dvector x
У	Pointer to dvector y

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 35 of file blas vec.c.

9.18.2.2 void fasp_blas_dvec_axpyz (const REAL a, dvector * x, dvector * y, dvector * z)

z = a*x + y, z is a third vector (z is cleared)

Parameters

а	REAL factor a
X	Pointer to dvector x
у	Pointer to dvector y
Z	Pointer to dvector z

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 87 of file blas_vec.c.

9.18.2.3 REAL fasp_blas_dvec_dotprod (dvector * x, dvector * y)

Inner product of two vectors (x,y)

Parameters

X	Pointer to dvector x
у	Pointer to dvector y

Returns

Inner product

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 123 of file blas_vec.c.

9.18.2.4 REAL fasp_blas_dvec_norm1 (dvector * x)

L1 norm of dvector x.

Parameters

x Pointer to dvector x	
------------------------	--

Returns

L1 norm of x

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 224 of file blas_vec.c.

9.18.2.5 **REAL** fasp_blas_dvec_norm2 (dvector * x)

L2 norm of dvector x.

Parameters

x Pointer to dvector x

Returns

L2 norm of x

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 267 of file blas_vec.c.

9.18.2.6 REAL fasp_blas_dvec_norminf (dvector * x)

Linf norm of dvector x.

Parameters

x Pointer to dvector x

Returns

L_inf norm of x

Author

Chensong Zhang

Date

07/01/209

Definition at line 307 of file blas_vec.c.

9.18.2.7 **REAL** fasp_blas_dvec_relerr (dvector * x, dvector * y)

Relative error of two dvector x and y.

Parameters

X	Pointer to dvector x
у	Pointer to dvector y

Returns

```
relative error ||x-y||/||x||
```

Author

Chensong Zhang

Date

07/01/209

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 169 of file blas_vec.c.

9.19 checkmat.c File Reference

Check matrix properties.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

INT fasp_check_diagpos (dCSRmat *A)

Check positivity of diagonal entries of a CSR sparse matrix.

SHORT fasp_check_diagzero (dCSRmat *A)

Check wether a CSR sparse matrix has diagonal entries that are very close to zero.

INT fasp_check_diagdom (dCSRmat *A)

Check whether a matrix is diagonal dominant.

INT fasp_check_symm (dCSRmat *A)

Check symmetry of a sparse matrix of CSR format.

SHORT fasp_check_dCSRmat (dCSRmat *A)

Check whether an dCSRmat matrix is valid or not.

SHORT fasp_check_iCSRmat (iCSRmat *A)

Check whether an iCSRmat matrix is valid or not.

9.19.1 Detailed Description

Check matrix properties.

Definition in file checkmat.c.

9.19.2 Function Documentation

9.19.2.1 SHORT fasp_check_dCSRmat (dCSRmat * A)

Check whether an dCSRmat matrix is valid or not.

Parameters

A Pointer to the matrix in dCSRmat format

Author

Shuo Zhang

Date

03/29/2009

Definition at line 276 of file checkmat.c.

9.19.2.2 INT fasp_check_diagdom (dCSRmat * A)

Check whether a matrix is diagonal dominant.

INT fasp_check_diagdom (dCSRmat *A)

Parameters

A Pointer to the dCSRmat matrix

Returns

Number of the rows which are diagonal dominant

Note

The routine chechs whether the sparse matrix is diagonal dominant on every row. It will print out the percentage of the rows which are diagonal dominant and which are not; the routine will return the number of the rows which are diagonal dominant.

Author

Shuo Zhang

Date

03/29/2009

Definition at line 109 of file checkmat.c.

9.19.2.3 INT fasp_check_diagpos (dCSRmat * A)

Check positivity of diagonal entries of a CSR sparse matrix.

Parameters

A Pointer to dCSRmat matrix

Returns

Number of negative diagonal entries

Author

Shuo Zhang

Date

03/29/2009

Definition at line 27 of file checkmat.c.

9.19.2.4 SHORT fasp_check_diagzero (dCSRmat * A)

Check wether a CSR sparse matrix has diagonal entries that are very close to zero.

Parameters

A pointr to the dCSRmat matrix

Returns

SUCCESS if no diagonal entry is clase to zero, else ERROR (negative value)

Author

Shuo Zhang

Date

03/29/2009

Definition at line 64 of file checkmat.c.

9.19.2.5 SHORT fasp_check_iCSRmat (iCSRmat * A)

Check whether an iCSRmat matrix is valid or not.

Parameters

A Pointer to the matrix in iCSRmat format

Author

Shuo Zhang

Date

03/29/2009

Definition at line 310 of file checkmat.c.

9.19.2.6 INT fasp_check_symm (dCSRmat * A)

Check symmetry of a sparse matrix of CSR format.

Parameters

A Pointer to the dCSRmat matrix

Returns

1 and 2 if the structure of the matrix is not symmetric; 0 if the structure of the matrix is symmetric,

Note

Print the maximal relative difference between matrix and its transpose.

Author

Shuo Zhang

Date

03/29/2009

Definition at line 154 of file checkmat.c.

9.20 coarsening_cr.c File Reference

Coarsening with Brannick-Falgout strategy.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

• INT fasp_amg_coarsening_cr (INT i_0, INT i_n, dCSRmat *A, ivector *vertices, AMG_param *param) CR coarsening.

9.20.1 Detailed Description

Coarsening with Brannick-Falgout strategy.

Definition in file coarsening_cr.c.

9.20.2 Function Documentation

```
9.20.2.1 INT fasp_amg_coarsening_cr ( INT i_0, INT i_n, dCSRmat * A, ivector * vertices, AMG_param * param )
```

CR coarsening.

Parameters

i_0	Starting index
i_n	Ending index
Α	Pointer to dCSRmat: the coefficient matrix (index starts from 0)
vertices	Pointer to CF, 0: fpt (current level) or 1: cpt
param	Pointer to AMG_param: AMG parameters

Author

James Brannick

Date

04/21/2010

Modified by Chunsheng Feng, Zheng Li

Date

10/14/2012

CR STAGES

Definition at line 41 of file coarsening_cr.c.

9.21 coarsening_rs.c File Reference

Coarsening with a modified Ruge-Stuben strategy.

```
#include "fasp.h"
#include "fasp_functs.h"
#include "linklist.inl"
```

Functions

• INT fasp_amg_coarsening_rs (dCSRmat *A, ivector *vertices, dCSRmat *P, iCSRmat *S, AMG_param *param) Standard and aggressive coarsening schemes.

9.21.1 Detailed Description

Coarsening with a modified Ruge-Stuben strategy.

Note

Ref Multigrid by U. Trottenberg, C. W. Oosterlee and A. Schuller Appendix P475 A.7 (by A. Brandt, P. Oswald and K. Stuben) Academic Press Inc., San Diego, CA, 2001.

Definition in file coarsening_rs.c.

9.21.2 Function Documentation

9.21.2.1 INT fasp_amg_coarsening_rs (dCSRmat * A, ivector * vertices, dCSRmat * P, iCSRmat * S, AMG_param * param)

Standard and aggressive coarsening schemes.

Parameters

Α	Pointer to dCSRmat: Coefficient matrix (index starts from 0)
vertices	Indicator vector for the C/F splitting of the variables
Р	Interpolation matrix (nonzero pattern only)
S	Strong connection matrix
param	Pointer to AMG_param: AMG parameters

Returns

SUCCESS or error message

Author

Xuehai Huang, Chensong Zhang, Xiaozhe Hu, Ludmil Zikatanov

Date

09/06/2010

Note

vertices = 0: fine; 1: coarse; 2: isolated or special

Modified by Xiaozhe Hu on 05/23/2011: add strength matrix as an argument Modified by Xiaozhe Hu on 04/24/2013: modfiy aggressive coarsening Modified by Chensong Zhang on 04/28/2013: remove linked list Modified by Chensong Zhang on 05/11/2013: restructure the code

Definition at line 56 of file coarsening_rs.c.

9.22 convert.c File Reference

Some utilities for format conversion.

```
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

• unsigned long fasp_aux_change_endian4 (unsigned long x)

Swap order for different endian systems.

double fasp_aux_change_endian8 (double x)

Swap order for different endian systems.

• double fasp_aux_bbyteToldouble (unsigned char bytes[])

Swap order of double-precision float for different endian systems.

INT endian_convert_int (const INT inum, const INT illength, const INT endianflag)

Swap order of an INT number.

REAL endian_convert_real (const REAL rnum, INT vlength, INT endianflag)

Swap order of a REAL number.

9.22.1 Detailed Description

Some utilities for format conversion.

Definition in file convert.c.

9.22.2 Function Documentation

9.22.2.1 INT endian_convert_int (const INT inum, const INT ilength, const INT endianflag)

Swap order of an INT number.

Parameters

ſ	inum	An INT value
Ī	ilength	Length of INT: 2 for short, 4 for int, 8 for long
Ī	endianflag	If endianflag = 1, it returns inum itself If endianflag = 2, it returns the swapped inum

Returns

Value of inum or swapped inum

Author

Ziteng Wang

Date

2012-12-24

Definition at line 105 of file convert.c.

9.22.2.2 REAL endian_convert_real (const REAL rnum, INT ilength, INT endianflag)

Swap order of a REAL number.

Parameters

rnum	An REAL value
ilength	Length of INT: 2 for short, 4 for int, 8 for long
endianflag	If endianflag = 1, it returns rnum itself If endianflag = 2, it returns the swapped rnum

Returns

Value of rnum or swapped rnum

Author

Ziteng Wang

Date

2012-12-24

Definition at line 137 of file convert.c.

9.22.2.3 double fasp_aux_bbyteToldouble (unsigned char bytes[])

Swap order of double-precision float for different endian systems.

Parameters

bytes	A unsigned char
- ,	

Returns

Unsigend long ineger after swapping

Author

Chensong Zhang

Date

11/16/2009

Definition at line 74 of file convert.c.

9.22.2.4 unsigned long fasp_aux_change_endian4 (unsigned long x)

Swap order for different endian systems.

Parameters

X	An unsigned long integer
---	--------------------------

Returns

Unsigend long ineger after swapping

Author

Chensong Zhang

Date

11/16/2009

Definition at line 25 of file convert.c.

9.22.2.5 double fasp_aux_change_endian8 (double x)

Swap order for different endian systems.

Parameters

X	A unsigned long integer

Returns

Unsigend long ineger after swapping

Author

Chensong Zhang

Date

11/16/2009

Definition at line 43 of file convert.c.

9.23 doxygen.h File Reference

Main page for Doygen documentation.

9.23.1 Detailed Description

Main page for Doygen documentation.

Definition in file doxygen.h.

9.24 eigen.c File Reference

Simple subroutines for compute the extreme eigenvalues.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

REAL fasp_dcsr_eig (dCSRmat *A, const REAL tol, const INT maxit)
 Approximate the largest eigenvalue of A by the power method.

9.24.1 Detailed Description

Simple subroutines for compute the extreme eigenvalues.

Definition in file eigen.c.

9.24.2 Function Documentation

```
9.24.2.1 REAL fasp_dcsr_eig ( dCSRmat * A, const REAL tol, const INT maxit )
```

Approximate the largest eigenvalue of A by the power method.

Parameters

Α	Pointer to the dCSRmat matrix
tol	Tolerance for stopping the power method
maxit	Max number of iterations

Returns

Largest eigenvalue

Author

Xiaozhe Hu

Date

01/25/2011

Definition at line 29 of file eigen.c.

9.25 factor.f File Reference

LU factoraization for CSR matrix.

Functions/Subroutines

- subroutine **sfactr** (ia, ja, n, iu, ju, ip, nwku)
- subroutine **sfactr_new** (ia, ja, n, iu, ju, ip, nwku, mem_chk)
- subroutine **factor** (ia, ja, n, iu, ju, ip, iup, an, ad, un, di)
- subroutine **forbac** (iu, ju, un, di, n, x)

9.25.1 Detailed Description

LU factoraization for CSR matrix.

Author

Ludmil Zikatanov

Date

01/01/2002

Definition in file factor.f.

9.26 famg.c File Reference

full AMG method as an iterative solver (main file)

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

```
    void fasp_solver_famg (dCSRmat *A, dvector *b, dvector *x, AMG_param *param)
    Solve Ax=b by full AMG.
```

9.26.1 Detailed Description

full AMG method as an iterative solver (main file)

Definition in file famg.c.

9.26.2 Function Documentation

```
9.26.2.1 void fasp_solver_famg ( dCSRmat * A, dvector * b, dvector * x, AMG_param * param )
```

Solve Ax=b by full AMG.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
param	Pointer to AMG_param: AMG parameters

Author

Xiaozhe Hu

Date

02/27/2011

Modified by Chensong Zhang on 01/10/2012 Modified by Chensong Zhang on 05/05/2013: Remove error handling for AMG setup

Definition at line 31 of file famg.c.

9.27 fasp.h File Reference

Main header file for FASP.

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include "messages.h"
```

Data Structures

struct ddenmat

Dense matrix of REAL type.

· struct idenmat

Dense matrix of INT type.

struct dCSRmat

Sparse matrix of REAL type in CSR format.

struct iCSRmat

Sparse matrix of INT type in CSR format.

struct dCOOmat

Sparse matrix of REAL type in COO (or IJ) format.

struct iCOOmat

Sparse matrix of INT type in COO (or IJ) format.

struct dCSRLmat

Sparse matrix of REAL type in CSRL format.

struct dSTRmat

Structure matrix of REAL type.

struct dvector

Vector with n entries of REAL type.

· struct ivector

Vector with n entries of INT type.

struct ILU_param

Parameters for ILU.

struct ILU_data

Data for ILU setup.

struct Schwarz param

Parameters for Schwarz method.

· struct Schwarz_data

Data for Schwarz methods.

struct AMG_param

Parameters for AMG solver.

· struct AMG data

Data for AMG solvers.

struct precond_data

Data passed to the preconditioners.

struct precond_data_str

Data passed to the preconditioner for dSTRmat matrices.

struct precond_diagstr

Data passed to diagnal preconditioner for dSTRmat matrices.

· struct precond

Preconditioner data and action.

· struct mxv matfree

Matrix-vector multiplication, replace the actual matrix.

struct input_param

Input parameters.

struct itsolver_param

Parameters passed to iterative solvers.

struct grid2d

Two dimensional grid data structure.

struct Link

Struct for Links.

struct linked_list

A linked list node.

Macros

- #define __FASP_HEADER_
- #define DEBUG_MODE OFF

Flags for developer's use only.

- #define CHMEM_MODE OFF
- #define DIAGONAL PREF OFF
- #define FASP_USE_ILU ON

For external software package support.

- #define DLMALLOC OFF
- #define NEDMALLOC OFF
- #define RS C1 ON

For internal code branches and data types.

- #define SHORT short
- #define INT int
- #define LONG long
- #define LONGLONG long long
- #define REAL double
- #define BIGREAL 1e+20

Some global constants.

- #define SMALLREAL 1e-20
- #define MAX REFINE LVL 20
- #define MAX AMG LVL 20
- #define STAG_RATIO 1e-4
- #define MAX_STAG 20
- #define MAX RESTART 20
- #define OPENMP HOLDS 2000
- #define MAX(a, b) (((a)>(b))?(a):(b))

Definition of max, min, abs.

- #define MIN(a, b) (((a)<(b))?(a):(b))
- #define ABS(a) (((a)>=0.0)?(a):-(a))
- #define GT(a, b) (((a)>(b))?(TRUE):(FALSE))

Definition of >, >=, <, <=, and isnan.

- #define GE(a, b) (((a)>=(b))?(TRUE):(FALSE))
- #define LS(a, b) (((a)<(b))?(TRUE):(FALSE))
- #define LE(a, b) (((a)<=(b))?(TRUE):(FALSE))
- #define ISNAN(a) (((a)!=(a))?(TRUE):(FALSE))
- #define ISTART 0

Index starting point: C convention or Fortran convention.

- #define N2C(ind) ((ind)-ISTART)
- #define C2N(ind) ((ind)+ISTART)
- #define FASP_GSRB 1

Typedefs

- typedef struct ddenmat ddenmat
- · typedef struct idenmat idenmat
- typedef struct dCSRmat dCSRmat
- typedef struct iCSRmat iCSRmat
- typedef struct dCOOmat dCOOmat
- typedef struct iCOOmat iCOOmat
- typedef struct dCSRLmat dCSRLmat
- typedef struct dSTRmat dSTRmat
- · typedef struct dvector dvector
- · typedef struct ivector ivector
- · typedef struct grid2d grid2d
- typedef grid2d * pgrid2d
- typedef const grid2d * pcgrid2d
- typedef struct linked_list ListElement
- typedef ListElement * LinkList

Variables

- unsigned INT total_alloc_mem
- unsigned INT total_alloc_count
- INT nx rb
- INT ny_rb
- INT nz rb
- INT * IMAP
- INT MAXIMAP

9.27.1 Detailed Description

Main header file for FASP. This header file contains general constants and data structures used in FASP.

Note

Only define macros and data structures, no function decorations.

Created by Chensong Zhang on 08/12/2010. Modified by Chensong Zhang on 12/13/2011.

Modified by Chensong Zhang on 12/25/2011.

Definition in file fasp.h.

9.27.2 Macro Definition Documentation

9.27.2.1 #define __FASP_HEADER__

indicate fasp.h has been included before

Definition at line 23 of file fasp.h.

9.27.2.2 #define ABS(a) (((a)>=0.0)?(a):-(a))

absolute value of a

Definition at line 74 of file fasp.h.

9.27.2.3 #define BIGREAL 1e+20

Some global constants.

A large real number

Definition at line 60 of file fasp.h.

9.27.2.4 #define C2N(ind) ((ind)+ISTART)

map from C index 0,1,... to Natural index 1,2,...

Definition at line 90 of file fasp.h.

9.27.2.5 #define CHMEM_MODE OFF

output MEMORY usage information

Definition at line 35 of file fasp.h.

9.27.2.6 #define DEBUG_MODE OFF

Flags for developer's use only.

output DEBUG information

Definition at line 33 of file fasp.h.

9.27.2.7 #define DIAGONAL_PREF OFF

order each row such that diagonal appears first

Definition at line 38 of file fasp.h.

9.27.2.8 #define DLMALLOC OFF

use dimalloc instead of standard malloc

Definition at line 44 of file fasp.h.

9.27.2.9 #define FASP_GSRB 1

MG level 0 use RedBlack Gauss Seidel Smoothing

Definition at line 1078 of file fasp.h.

9.27.2.10 #define FASP_USE_ILU ON

For external software package support.

enable ILU or not

Definition at line 43 of file fasp.h.

9.27.2.11 #define GE(a, b) (((a)>=(b))?(TRUE):(FALSE))

is $a \ge b$?

Definition at line 80 of file fasp.h.

9.27.2.12 #define GT(a, b) (((a)>(b))?(TRUE):(FALSE))

Definition of >, >=, <, <=, and isnan.

is a > b?

Definition at line 79 of file fasp.h.

9.27.2.13 #define INT int

regular integer type: int or long

Definition at line 52 of file fasp.h.

9.27.2.14 #define ISNAN(a) (((a)!=(a))?(TRUE):(FALSE))

is a == NAN?

Definition at line 83 of file fasp.h.

9.27.2.15 #define ISTART 0

Index starting point: C convention or Fortran convention.

0 if in Natural index, 1 if data is in C index

Definition at line 88 of file fasp.h.

9.27.2.16 #define LE(a, b) (((a)<=(b))?(TRUE):(FALSE))

is a \leq = b?

Definition at line 82 of file fasp.h.

9.27.2.17 #define LONG long

long integer type

Definition at line 53 of file fasp.h.

9.27.2.18 #define LONGLONG long long

long integer type

Definition at line 54 of file fasp.h.

9.27.2.19 #define LS(a, b) (((a)<(b))?(TRUE):(FALSE))

is a < b?

Definition at line 81 of file fasp.h.

9.27.2.20 #define MAX(a, b) (((a)>(b))?(a):(b))

Definition of max, min, abs.

bigger one in a and b

Definition at line 72 of file fasp.h.

9.27.2.21 #define MAX_AMG_LVL 20

Maximal AMG coarsening level

Definition at line 63 of file fasp.h.

9.27.2.22 #define MAX_REFINE_LVL 20

Maximal refinement level

Definition at line 62 of file fasp.h.

9.27.2.23 #define MAX_RESTART 20

Maximal number of restarting

Definition at line 66 of file fasp.h.

9.27.2.24 #define MAX_STAG 20

Maximal number of staganation times

Definition at line 65 of file fasp.h.

9.27.2.25 #define MIN(a, b) (((a)<(b))?(a):(b))

smaller one in a and b

Definition at line 73 of file fasp.h.

9.27.2.26 #define N2C(ind) ((ind)-ISTART)

map from Natural index 1,2,... to C index 0,1,...

Definition at line 89 of file fasp.h.

9.27.2.27 #define NEDMALLOC OFF

use nedmalloc instead of standard malloc

Definition at line 45 of file fasp.h.

9.27.2.28 #define OPENMP_HOLDS 2000

Switch to sequence or openmp

Definition at line 67 of file fasp.h.

9.27.2.29 #define REAL double

float type

Definition at line 55 of file fasp.h.

9.27.2.30 #define RS_C1 ON

For internal code branches and data types.

CF splitting of RS: check C1 Criterion

Definition at line 50 of file fasp.h.

9.27.2.31 #define SHORT short

short integer type

Definition at line 51 of file fasp.h.

9.27.2.32 #define SMALLREAL 1e-20

A small real number

Definition at line 61 of file fasp.h.

9.27.2.33 #define STAG_RATIO 1e-4

Staganation tolerance = tol*STAGRATIO

Definition at line 64 of file fasp.h.

- 9.27.3 Typedef Documentation
- 9.27.3.1 typedef struct dCOOmat dCOOmat

Sparse matrix of REAL type in COO format

9.27.3.2 typedef struct dCSRLmat dCSRLmat

Sparse matrix of REAL type in CSRL format

9.27.3.3 typedef struct dCSRmat dCSRmat

Sparse matrix of REAL type in CSR format

9.27.3.4 typedef struct ddenmat ddenmat

Dense matrix of REAL type

9.27.3.5 typedef struct dSTRmat dSTRmat

Structured matrix of REAL type

9.27.3.6 typedef struct dvector dvector

Vector of REAL type

9.27.3.7 typedef struct grid2d grid2d

2D grid type for plotting

9.27.3.8 typedef struct iCOOmat iCOOmat

Sparse matrix of INT type in COO format

9.27.3.9 typedef struct iCSRmat iCSRmat

Sparse matrix of INT type in CSR format

9.27.3.10 typedef struct idenmat idenmat

Dense matrix of INT type

9.27.3.11 typedef struct ivector ivector

Vector of INT type

9.27.3.12 typedef ListElement* LinkList

List of linkslinked list

Definition at line 1073 of file fasp.h.

9.27.3.13 typedef struct linked_list ListElement

Linked element in list

9.27.3.14 typedef const grid2d* pcgrid2d

Grid in 2d

Definition at line 1027 of file fasp.h.

9.27.3.15 typedef grid2d* pgrid2d

Grid in 2d

Definition at line 1025 of file fasp.h.

9.27.4 Variable Documentation

9.27.4.1 INT* IMAP

Red Black Gs Smoother imap

9.27.4.2 **INT MAXIMAP**

Red Black Gs Smoother max dofs of reservoir

9.27.4.3 INT nx_rb

Red Black Gs Smoother Nx

9.27.4.4 INT ny_rb

Red Black Gs Smoother Ny

9.27.4.5 INT nz_rb

Red Black Gs Smoother Nz

9.27.4.6 unsigned INT total_alloc_count

total allocation times

Definition at line 33 of file memory.c.

9.27.4.7 unsigned INT total_alloc_mem

total allocated memory

Definition at line 32 of file memory.c.

9.28 fasp_block.h File Reference

Main header file for FASP (block matrices)

#include "fasp.h"

Data Structures

struct dBSRmat

Block sparse row storage matrix of REAL type.

struct block dCSRmat

Block REAL CSR matrix format.

struct block_iCSRmat

Block INT CSR matrix format.

struct block dvector

Block REAL vector structure.

· struct block ivector

Block INT vector structure.

struct block_Reservoir

Block REAL matrix format for reservoir simulation.

struct block_BSR

Block REAL matrix format for reservoir simulation.

struct AMG_data_bsr

Data for multigrid levels. (BSR format)

struct precond_diagbsr

Data passed to diagnal preconditioner for dBSRmat matrices.

• struct precond_data_bsr

Data passed to the preconditioners.

struct precond_block_reservoir_data

Data passed to the preconditioner for preconditioning reservoir simulation problems.

struct precond_block_data

Data passed to the preconditioner for block diagonal preconditioning.

· struct precond FASP blkoil data

Data passed to the preconditioner for preconditioning reservoir simulation problems.

Typedefs

- typedef struct dBSRmat dBSRmat
- typedef struct block_dCSRmat block_dCSRmat
- typedef struct block iCSRmat block iCSRmat
- typedef struct block_dvector block_dvector

- typedef struct block_ivector block_ivector
- · typedef struct block Reservoir block Reservoir
- typedef struct block BSR block BSR
- typedef struct precond_block_reservoir_data precond_block_reservoir_data

9.28.1 Detailed Description

Main header file for FASP (block matrices)

Note

This header file contains definitions of block matrices, including grid-major type and variable-major type. In this header, we only define macros and data structures, not function decorations.

Created by Chensong Zhang on 05/21/2010. Modified by Xiaozhe Hu on 05/28/2010: add precond_block_reservoir_data. Modified by Xiaozhe Hu on 06/15/2010: modify precond_block_reservoir_data. Modified by Chensong Zhang on 10/11/2010: add BSR data.

Modified by Chensong Zhang on 10/17/2012: modify comments.

Definition in file fasp block.h.

9.28.2 Typedef Documentation

9.28.2.1 typedef struct block BSR block BSR

Block of BSR matrices of REAL type

9.28.2.2 typedef struct block_dCSRmat block_dCSRmat

Matrix of REAL type in Block CSR format

9.28.2.3 typedef struct block_dvector block_dvector

Vector of REAL type in Block format

9.28.2.4 typedef struct block_iCSRmat block_iCSRmat

Matrix of INT type in Block CSR format

9.28.2.5 typedef struct block_ivector block_ivector

Vector of INT type in Block format

9.28.2.6 typedef struct block_Reservoir block_Reservoir

Special block matrix for Reservoir Simulation

9.28.2.7 typedef struct dBSRmat dBSRmat

Matrix of REAL type in BSR format

9.28.2.8 typedef struct precond block reservoir data precond block reservoir data

Precond data for Reservoir Simulation

9.29 fmgcycle.c File Reference

Abstract non-recursive full multigrid cycle.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "forts_ns.h"
#include "mg_util.inl"
```

Functions

• void fasp_solver_fmgcycle (AMG_data *mgl, AMG_param *param)

Solve Ax=b with non-recursive full multigrid K-cycle.

9.29.1 Detailed Description

Abstract non-recursive full multigrid cycle.

Definition in file fmgcycle.c.

9.29.2 Function Documentation

```
9.29.2.1 void fasp_solver_fmgcycle ( AMG_data * mgl, AMG_param * param )
```

Solve Ax=b with non-recursive full multigrid K-cycle.

Parameters

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

Author

Chensong Zhang

Date

02/27/2011

Modified by Chensong Zhang on 06/01/2012: fix a bug when there is only one level. Modified by Chensong Zhang on 02/27/2013: update direct solvers.

Definition at line 34 of file fmgcycle.c.

9.30 formats.c File Reference

Matrix format conversion routines.

```
#include "fasp.h"
#include "fasp_block.h"
#include "fasp_functs.h"
```

Functions

SHORT fasp_format_dcoo_dcsr (dCOOmat *A, dCSRmat *B)

Transform a REAL matrix from its IJ format to its CSR format.

• SHORT fasp_format_dcsr_dcoo (dCSRmat *A, dCOOmat *B)

Transform a REAL matrix from its CSR format to its IJ format.

SHORT fasp_format_dstr_dcsr (dSTRmat *A, dCSRmat *B)

Transfer a 'dSTRmat' type matrix into a 'dCSRmat' type matrix.

dCSRmat fasp_format_bdcsr_dcsr (block_dCSRmat *Ab)

Form the whole dCSRmat A using blocks given in Ab.

dCSRLmat * fasp_format_dcsrl_dcsr (dCSRmat *A)

Convert a dCSRmat into a dCSRLmat.

dCSRmat fasp_format_dbsr_dcsr (dBSRmat *B)

Transfer a 'dBSRmat' type matrix into a dCSRmat.

dBSRmat fasp_format_dcsr_dbsr (dCSRmat *B, const INT nb)

Transfer a dCSRmat type matrix into a dBSRmat.

dBSRmat fasp format dstr dbsr (dSTRmat *B)

Transfer a 'dSTRmat' type matrix to a 'dBSRmat' type matrix.

dCOOmat * fasp_format_dbsr_dcoo (dBSRmat *B)

Transfer a 'dBSRmat' type matrix to a 'dCOOmat' type matrix.

9.30.1 Detailed Description

Matrix format conversion routines.

Definition in file formats.c.

9.30.2 Function Documentation

9.30.2.1 dCSRmat fasp_format_bdcsr_dcsr (block_dCSRmat * Ab)

Form the whole dCSRmat A using blocks given in Ab.

Parameters

Ab Pointer to block_dCSRmat matrix

Returns

dCSRmat matrix if succeed, NULL if fail

Author

Shiquan Zhang

Date

08/10/2010

Definition at line 293 of file formats.c.

9.30.2.2 dCOOmat * fasp_format_dbsr_dcoo (dBSRmat * B)

Transfer a 'dBSRmat' type matrix to a 'dCOOmat' type matrix.

Parameters

B Pointer to dBSRmat matrix

Returns

Pointer to dCOOmat matrix

Author

Zhiyang Zhou

Date

2010/10/26

Definition at line 956 of file formats.c.

9.30.2.3 dCSRmat fasp_format_dbsr_dcsr (dBSRmat * B)

Transfer a 'dBSRmat' type matrix into a dCSRmat.

Parameters

B Pointer to dBSRmat matrix

Returns

dCSRmat matrix

Author

Zhiyang Zhou

Date

10/23/2010

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/24/2012

Note

Works for general nb (Xiaozhe)

Definition at line 496 of file formats.c.

9.30.2.4 SHORT fasp_format_dcoo_dcsr (dCOOmat * A, dCSRmat * B)

Transform a REAL matrix from its IJ format to its CSR format.

Parameters

Α	Pointer to dCOOmat matrix
В	Pointer to dCSRmat matrix

Returns

SUCCESS if succeed

Author

Xuehai Huang

Date

08/10/2009

Definition at line 28 of file formats.c.

9.30.2.5 dBSRmat fasp_format_dcsr_dbsr (dCSRmat * B, const INT nb)

Transfer a dCSRmat type matrix into a dBSRmat.

Parameters

В	Pointer to the dCSRmat type matrix
nb	size of each block

Returns

dBSRmat matrix

Author

Changhe Qiao

Date

03/12/2012

Modified by Xiaozhe Hu on 03/13/2012 Modified by Chunsheng Feng, Zheng Li on 10/13/2012 Definition at line 721 of file formats.c.

9.30.2.6 SHORT fasp_format_dcsr_dcoo (dCSRmat * A, dCOOmat * B)

Transform a REAL matrix from its CSR format to its IJ format.

Parameters

Α	Pointer to dCSRmat matrix
В	Pointer to dCOOmat matrix

Returns

SUCCESS if succeed

Author

Xuehai Huang

Date

08/10/2009

Modified by Chunsheng Feng, Zheng Li

Date

10/12/2012

Definition at line 81 of file formats.c.

9.30.2.7 dCSRLmat * fasp_format_dcsrl_dcsr (dCSRmat * A)

Convert a dCSRmat into a dCSRLmat.

Parameters

A Pointer to dCSRLmat matrix

Returns

Pointer to dCSRLmat matrix

Author

Zhiyang Zhou

Date

2011/01/07

Definition at line 362 of file formats.c.

9.30.2.8 dBSRmat fasp_format_dstr_dbsr (dSTRmat * B)

Transfer a 'dSTRmat' type matrix to a 'dBSRmat' type matrix.

Parameters

В	Pointer to dSTRmat matrix
---	---------------------------

Returns

dBSRmat matrix

Author

Zhiyang Zhou

Date

2010/10/26

Definition at line 852 of file formats.c.

9.30.2.9 SHORT fasp_format_dstr_dcsr (dSTRmat * A, dCSRmat * B)

Transfer a 'dSTRmat' type matrix into a 'dCSRmat' type matrix.

Parameters

Α	Pointer to dSTRmat matrix
В	Pointer to dCSRmat matrix

Returns

SUCCESS if succeed

Author

Zhiyang Zhou

Date

2010/04/29

Definition at line 118 of file formats.c.

9.31 givens.c File Reference

Givens transformation.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

• void fasp_aux_givens (const REAL beta, dCSRmat *H, dvector *y, REAL *tmp)

Perform Givens rotations to compute y | beta*e_1- H*y|.

9.31.1 Detailed Description

Givens transformation.

Definition in file givens.c.

9.31.2 Function Documentation

```
9.31.2.1 void fasp_aux_givens ( const REAL beta, dCSRmat * H, dvector * y, REAL * tmp )
```

Perform Givens rotations to compute y |beta*e_1- H*y|.

Parameters

beta	Norm of residual r_0
Н	(m+1)*m upper Hessenberg dCSRmat matrix
у	Minimizer of beta*e_1- H*y
tmp	Temporary work array

Author

Xuehai Huang

Date

10/19/2008

Definition at line 28 of file givens.c.

9.32 gmg_poisson.c File Reference

GMG method as an iterative solver for Poisson Problem.

```
#include <time.h>
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "gmg_util.inl"
```

Functions

INT fasp_poisson_gmg_1D (REAL *u, REAL *b, INT nx, INT maxlevel, REAL rtol, const SHORT prtlvl)
 Solve Ax=b of Poisson 1D equation by Geometric Multigrid Method.

- INT fasp_poisson_gmg_2D (REAL *u, REAL *b, INT nx, INT ny, INT maxlevel, REAL rtol, const SHORT prtlvl)

 Solve Ax=b of Poisson 2D equation by Geometric Multigrid Method.
- INT fasp_poisson_gmg_3D (REAL *u, REAL *b, INT nx, INT ny, INT nz, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 3D equation by Geometric Multigrid Method.

- void fasp_poisson_fgmg_1D (REAL *u, REAL *b, INT nx, INT maxlevel, REAL rtol, const SHORT prtlvl)

 Solve Ax=b of Poisson 1D equation by Geometric Multigrid Method (Full Multigrid)
- void fasp_poisson_fgmg_2D (REAL *u, REAL *b, INT nx, INT ny, INT maxlevel, REAL rtol, const SHORT prtlvl)

 Solve Ax=b of Poisson 2D equation by Geometric Multigrid Method (Full Multigrid)
- void fasp_poisson_fgmg_3D (REAL *u, REAL *b, INT nx, INT ny, INT nz, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 3D equation by Geometric Multigrid Method (Full Multigrid)

- INT fasp_poisson_pcg_gmg_1D (REAL *u, REAL *b, INT nx, INT maxlevel, REAL rtol, const SHORT prtlvl)

 Solve Ax=b of Poisson 1D equation by Geometric Multigrid Method (GMG preconditioned Conjugate Gradient method)
- INT fasp_poisson_pcg_gmg_2D (REAL *u, REAL *b, INT nx, INT ny, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 2D equation by Geometric Multigrid Method (GMG preconditioned Conjugate Gradient method)

• INT fasp_poisson_pcg_gmg_3D (REAL *u, REAL *b, INT nx, INT ny, INT nz, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 3D equation by Geometric Multigrid Method (GMG preconditioned Conjugate Gradient method)

9.32.1 Detailed Description

GMG method as an iterative solver for Poisson Problem.

Definition in file gmg poisson.c.

9.32.2 Function Documentation

9.32.2.1 void fasp_poisson_fgmg_1D (REAL * u, REAL * b, INT nx, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 1D equation by Geometric Multigrid Method (Full Multigrid)

Parameters

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

Author

Ziteng Wang

Date

06/07/2013

Definition at line 417 of file gmg_poisson.c.

9.32.2.2 void fasp_poisson_fgmg_2D (REAL * u, REAL * b, INT nx, INT ny, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 2D equation by Geometric Multigrid Method (Full Multigrid)

Parameters

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
ny	Number of grids in Y direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

Author

Ziteng Wang

Date

06/07/2013

Definition at line 509 of file gmg_poisson.c.

9.32.2.3 void fasp_poisson_fgmg_3D (REAL * u, REAL * b, INT nx, INT ny, INT nz, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 3D equation by Geometric Multigrid Method (Full Multigrid)

Parameters

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
ny	NUmber of grids in y direction
nz	NUmber of grids in z direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

Author

Ziteng Wang

Date

06/07/2013

Definition at line 616 of file gmg_poisson.c.

9.32.2.4 INT fasp_poisson_gmg_1D (REAL * u, REAL * b, INT nx, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 1D equation by Geometric Multigrid Method.

Parameters

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

Author

Ziteng Wang

Date

06/07/2013

Definition at line 34 of file gmg poisson.c.

9.32.2.5 INT fasp_poisson_gmg_2D (REAL * u, REAL * b, INT nx, INT ny, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 2D equation by Geometric Multigrid Method.

Parameters

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
ny	Number of grids in y direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

Author

Ziteng Wang

Date

06/07/2013

Definition at line 154 of file gmg_poisson.c.

9.32.2.6 INT fasp_poisson_gmg_3D (REAL * u, REAL * b, INT nx, INT ny, INT nz, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 3D equation by Geometric Multigrid Method.

Parameters

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
ny	Number of grids in y direction
nz	Number of grids in z direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

Author

Ziteng Wang

Date

06/07/2013

Definition at line 285 of file gmg_poisson.c.

9.32.2.7 INT fasp_poisson_pcg_gmg_1D (REAL * u, REAL * b, INT nx, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 1D equation by Geometric Multigrid Method (GMG preconditioned Conjugate Gradient method)

Parameters

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

Author

Ziteng Wang

Date

06/07/2013

Definition at line 723 of file gmg_poisson.c.

9.32.2.8 INT fasp_poisson_pcg_gmg_2D (REAL * u, REAL * b, INT nx, INT ny, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 2D equation by Geometric Multigrid Method (GMG preconditioned Conjugate Gradient method)

Parameters

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
ny	Number of grids in y direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

Author

Ziteng Wang

Date

06/07/2013

Definition at line 813 of file gmg_poisson.c.

9.32.2.9 INT fasp_poisson_pcg_gmg_3D (REAL * u, REAL * b, INT nx, INT ny, INT nz, INT maxlevel, REAL rtol, const SHORT prtlvl)

Solve Ax=b of Poisson 3D equation by Geometric Multigrid Method (GMG preconditioned Conjugate Gradient method)

Parameters

и	Pointer to the vector of dofs
b	Pointer to the vector of right hand side
nx	Number of grids in x direction
ny	Number of grids in y direction
nz	Number of grids in z direction
maxlevel	Maximum levels of the multigrid
rtol	Relative tolerance to judge convergence
prtlvl	Print level for output

Author

Ziteng Wang

Date

06/07/2013

Definition at line 918 of file gmg_poisson.c.

9.33 gmg_util.inl File Reference

Routines for GMG solvers.

9.33.1 Detailed Description

Routines for GMG solvers.

Definition in file gmg_util.inl.

9.34 graphics.c File Reference

Functions for graphical output.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void fasp_dcsr_subplot (const dCSRmat *A, const char *filename, INT size)

Write sparse matrix pattern in BMP file format.

- void fasp_dbsr_subplot (const dBSRmat *A, const char *filename, INT size)
- void fasp_grid2d_plot (pgrid2d pg, INT level)

Output grid to a EPS file.

INT fasp_dbsr_plot (const dBSRmat *A, const char *fname)

Write dBSR sparse matrix pattern in BMP file format.

• INT fasp_dcsr_plot (const dCSRmat *A, const char *fname)

9.34.1 Detailed Description

Functions for graphical output.

Definition in file graphics.c.

9.34.2 Function Documentation

```
9.34.2.1 void fasp_dbsr_plot ( const dBSRmat * A, const char * filename )
```

Write dBSR sparse matrix pattern in BMP file format.

Parameters

Α	Pointer to the dBSRmat matrix
filename	File name

Author

Chunsheng Feng

Date

11/16/2013

Note

The routine fasp_dbsr_plot writes pattern of the specified dBSRmat matrix in uncompressed BMP file format (Windows bitmap) to a binary file whose name is specified by the character string filename.

Each pixel corresponds to one matrix element. The pixel colors have the following meaning:

White structurally zero element Black zero element Blue positive element Red negative element Brown nearly zero element

Definition at line 466 of file graphics.c.

9.34.2.2 void fasp_dcsr_subplot (const dCSRmat * A, const char * filename, INT size)

Write sparse matrix pattern in BMP file format.

Parameters

Α	Pointer to the dCSRmat matrix
filename	File name
size	size*size is the picture size for the picture

Author

Chensong Zhang

Date

03/29/2009

Note

The routine fasp_dcsr_subplot writes pattern of the specified dCSRmat matrix in uncompressed BMP file format (Windows bitmap) to a binary file whose name is specified by the character string filename.

Each pixel corresponds to one matrix element. The pixel colors have the following meaning:

White structurally zero element Blue positive element Red negative element Brown nearly zero element Definition at line 44 of file graphics.c.

9.34.2.3 void fasp_grid2d_plot (pgrid2d pg, INT level)

Output grid to a EPS file.

Parameters

pg	Pointer to grid in 2d
level	Number of levels

Author

Chensong Zhang

Date

03/29/2009

Definition at line 175 of file graphics.c.

9.35 ilu.f File Reference

ILU routines for preconditioning adapted from SPARSEKIT.

Functions/Subroutines

- subroutine iluk (n, a, ja, ia, lfil, alu, jlu, iwk, ierr, nzlu)
- subroutine ilut (n, a, ja, ia, lfil, droptol, alu, jlu, iwk, ierr, nz)
- subroutine ilutp (n, a, ja, ia, lfil, droptol, permtol, mbloc, alu, jlu, iwk, ierr, nz)
- subroutine **srtr** (num, q)
- subroutine **qsplit** (a, ind, n, ncut)
- subroutine symbfactor (n, colind, rwptr, levfill, nzmax, nzlu, ijlu, uptr, ierr)

9.35.1 Detailed Description

ILU routines for preconditioning adapted from SPARSEKIT.

Note

Incomplete Factorization Methods: ILUk, ILUt, ILUtp

Definition in file ilu.f.

9.36 ilu_setup_bsr.c File Reference

Setup Incomplete LU decomposition for dBSRmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

- void symbfactor_ (const INT *n, INT *colind, INT *rwptr, const INT *levfill, const INT *nzmax, INT *nzlu, INT *ijlu, INT *uptr, INT *ierr)
- SHORT fasp_ilu_dbsr_setup (dBSRmat *A, ILU_data *iludata, ILU_param *iluparam)

Get ILU decoposition of a BSR matrix A.

9.36.1 Detailed Description

Setup Incomplete LU decomposition for dBSRmat matrices.

Definition in file ilu setup bsr.c.

- 9.36.2 Function Documentation
- $9.36.2.1 \quad \textbf{SHORT fasp_ilu_dbsr_setup (dBSRmat * \textit{A, ILU_data} * \textit{iludata, ILU_param} * \textit{iluparam})}$

Get ILU decoposition of a BSR matrix A.

Parameters

	Α	Pointer to dBSRmat matrix
	iludata	Pointer to ILU_data
Ì	iluparam	Pointer to ILU_param

Author

Shiquan Zhang, Xiaozhe Hu

Date

11/08/2010

Note

Works for general nb (Xiaozhe)

Definition at line 42 of file ilu_setup_bsr.c.

9.37 ilu_setup_csr.c File Reference

Setup of ILU decomposition for dCSRmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

- void iluk_ (const INT *n, REAL *a, INT *ja, INT *ia, INT *lfil, REAL *alu, INT *jlu, INT *iwk, INT *ierr, INT *nzlu)
- void ilut_ (const INT *n, REAL *a, INT *ja, INT *ia, INT *lfil, const REAL *droptol, REAL *alu, INT *jlu, INT *iwk, INT *ierr, INT *nz)
- void ilutp_ (const INT *n, REAL *a, INT *ja, INT *ia, INT *lfil, const REAL *droptol, const REAL *permtol, const INT *mbloc, REAL *alu, INT *jlu, INT *iwk, INT *ierr, INT *nz)
- SHORT fasp_ilu_dcsr_setup (dCSRmat *A, ILU_data *iludata, ILU_param *iluparam)

Get ILU decoposition of a CSR matrix A.

9.37.1 Detailed Description

Setup of ILU decomposition for dCSRmat matrices.

Definition in file ilu_setup_csr.c.

9.37.2 Function Documentation

9.37.2.1 SHORT fasp_ilu_dcsr_setup (dCSRmat * A, ILU_data * iludata, ILU_param * iluparam)

Get ILU decoposition of a CSR matrix A.

Parameters

Α	Pointer to dCSRmat matrix
iludata	Pointer to ILU_data
iluparam	Pointer to ILU_param

Author

Shiquan Zhang

Date

12/27/2009

Definition at line 48 of file ilu_setup_csr.c.

9.38 ilu_setup_str.c File Reference

Setup of ILU decomposition for dSTRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

```
    void fasp_ilu_dstr_setup0 (dSTRmat *A, dSTRmat *LU)
```

Get ILU(0) decomposition of a structured matrix A.

void fasp_ilu_dstr_setup1 (dSTRmat *A, dSTRmat *LU)

Get ILU(1) decoposition of a structured matrix A.

9.38.1 Detailed Description

Setup of ILU decomposition for dSTRmat matrices.

Definition in file ilu_setup_str.c.

9.38.2 Function Documentation

```
9.38.2.1 void fasp_ilu_dstr_setup0 ( dSTRmat * A, dSTRmat * LU )
```

Get ILU(0) decomposition of a structured matrix A.

Parameters

A Pointer to dSTRmat

H	Pointer to ILU structured matrix of REAL type

Author

Shiquan Zhang, Xiaozhe Hu

Date

11/08/2010

Note

Only works for 5 bands 2D and 7 bands 3D matrix with default offsets (order can be arbitrary)!

Definition at line 28 of file ilu_setup_str.c.

```
9.38.2.2 void fasp_ilu_dstr_setup1 ( dSTRmat * A, dSTRmat * LU )
```

Get ILU(1) decoposition of a structured matrix A.

Parameters

Α	Pointer to oringinal structured matrix of REAL type
LU	Pointer to ILU structured matrix of REAL type

Author

Shiquan Zhang, Xiaozhe Hu

Date

11/08/2010

Note

put L and U in a STR matrix and it has the following structure: the diag is d, the offdiag of L are alpha1 to alpha6, the offdiag of U are beta1 to beta6

Only works for 5 bands 2D and 7 bands 3D matrix with default offsets

Definition at line 319 of file ilu_setup_str.c.

9.39 init.c File Reference

Initialize important data structures.

```
#include "fasp.h"
#include "fasp_functs.h"
```

9.39 init.c File Reference 173

Functions

AMG data * fasp amg data create (SHORT max levels)

Create and initialize AMG_data for classical and SA AMG.

AMG_data_bsr * fasp_amg_data_bsr_create (SHORT max_levels)

Create and initialize AMG data data sturcture for AMG/SAMG (BSR format)

• void fasp_ilu_data_alloc (INT iwk, INT nwork, ILU_data *iludata)

Allocate workspace for ILU factorization.

void fasp_schwarz_data_free (Schwarz_data *schwarz)

Free Schwarz_data data memeory space.

void fasp_amg_data_free (AMG_data *mgl, AMG_param *param)

Free AMG_data data memeory space.

void fasp_amg_data_bsr_free (AMG_data_bsr *mgl)

Free AMG_data_bsr data memeory space.

void fasp_ilu_data_free (ILU_data *ILUdata)

Create ILU_data sturcture.

void fasp_ilu_data_null (ILU_data *ILUdata)

Initialize ILU data.

void fasp_precond_null (precond *pcdata)

Initialize precond data.

9.39.1 Detailed Description

Initialize important data structures.

Note

Every structures should be initialized before usage.

Definition in file init.c.

9.39.2 Function Documentation

9.39.2.1 AMG_data_bsr * fasp_amg_data_bsr_create (SHORT max_levels)

Create and initialize AMG_data data sturcture for AMG/SAMG (BSR format)

Parameters

max_levels | Max number of levels allowed

Returns

Pointer to the AMG_data data structure

Author

Xiaozhe Hu

Date

08/07/2011

Definition at line 54 of file init.c.

9.39.2.2 void fasp_amg_data_bsr_free (AMG_data_bsr * mgl)

Free AMG_data_bsr data memeory space.

Parameters

mgl Pointer to the AMG_data_bsr

Author

Xiaozhe Hu

Date

2013/02/13

Definition at line 184 of file init.c.

9.39.2.3 AMG_data * fasp_amg_data_create (SHORT max_levels)

Create and initialize AMG_data for classical and SA AMG.

Parameters

max_levels	Max number of levels allowed
------------	------------------------------

Returns

Pointer to the AMG_data data structure

Author

Chensong Zhang

Date

2010/04/06

Definition at line 27 of file init.c.

9.39.2.4 void fasp_amg_data_free (AMG_data * mgl, AMG_param * param)

Free AMG_data data memeory space.

Parameters

	mgl	Pointer to the AMG_data
Ì	param	Pointer to AMG parameters

Author

Chensong Zhang

9.39 init.c File Reference 175

Date

2010/04/06

Modified by Chensong Zhang on 05/05/2013: Clean up param as well!

Definition at line 137 of file init.c.

9.39.2.5 void fasp_ilu_data_alloc (INT iwk, INT nwork, ILU_data * iludata)

Allocate workspace for ILU factorization.

Parameters

	iwk	Size of the index array
	nwork	Size of the work array
Ī	iludata	Pointer to the ILU_data

Author

Chensong Zhang

Date

2010/04/06

Definition at line 82 of file init.c.

9.39.2.6 void fasp_ilu_data_free (ILU_data * ILUdata)

Create ILU_data sturcture.

Parameters

ILUdata	Pointer to ILU_data
---------	---------------------

Author

Chensong Zhang

Date

2010/04/03

Definition at line 229 of file init.c.

9.39.2.7 void fasp_ilu_data_null (ILU_data * ILUdata)

Initialize ILU data.

Parameters

ILUdata Pointer to ILU_data

Author

Chensong Zhang

Date

2010/03/23

Definition at line 250 of file init.c.

9.39.2.8 void fasp_precond_null (precond * pcdata)

Initialize precond data.

Parameters

pcdata Pointer to precond

Author

Chensong Zhang

Date

2010/03/23

Definition at line 266 of file init.c.

9.39.2.9 void fasp_schwarz_data_free (Schwarz_data * schwarz)

Free Schwarz_data data memeory space.

Parameters

*schwarz | pointer to the AMG_data data

Author

Xiaozhe Hu

Date

2010/04/06

Definition at line 108 of file init.c.

9.40 input.c File Reference

Read input parameters.

```
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void fasp_param_input (char *filenm, input_param *Input)
 Read input parameters from disk file.

9.40.1 Detailed Description

Read input parameters.

Definition in file input.c.

9.40.2 Function Documentation

```
9.40.2.1 void fasp_param_input ( char * filenm, input_param * Input )
```

Read input parameters from disk file.

Parameters

filenm	File name for input file
Input	Input parameters

Author

Chensong Zhang

Date

03/20/2010

Modified by Xiaozhe Hu on 01/23/2011: add AMLI cycle Modified by Chensong Zhang on 01/10/2012 Modified by Ludmil Zikatanov on 02/15/2013 Modified by Chensong Zhang on 05/10/2013: add a new input.

Definition at line 29 of file input.c.

9.41 interface mumps.c File Reference

Interface to MUMPS direct solvers.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

- int fasp_solver_mumps (dCSRmat *ptrA, dvector *b, dvector *u, const int print_level)
 Solve Ax=b by MUMPS directly.
- int fasp_solver_mumps_steps (dCSRmat *ptrA, dvector *b, dvector *u, const int job)

 Solve Ax=b by MUMPS in three steps.

9.41.1 Detailed Description

Interface to MUMPS direct solvers.

Definition in file interface_mumps.c.

9.41.2 Function Documentation

9.41.2.1 int fasp_solver_mumps (dCSRmat * ptrA, dvector * b, dvector * u, const int print_level)

Solve Ax=b by MUMPS directly.

Parameters

ptrA	Pointer to a dCSRmat matrix
b	Pointer to the dvector of right-hand side term
и	Pointer to the dvector of solution
print_level	Output level

Author

Chunsheng Feng

Date

02/27/2013

Modified by Chensong Zhang on 02/27/2013 for new FASP function names.

Definition at line 35 of file interface_mumps.c.

9.41.2.2 int fasp_solver_mumps_steps (dCSRmat * ptrA, dvector * b, dvector * u, const int job)

Solve Ax=b by MUMPS in three steps.

Parameters

ptrA	Pointer to a dCSRmat matrix
b	Pointer to the dvector of right-hand side term
и	Pointer to the dvector of solution
job	1: Setup, 2: Sovle, 3 Destroy

Author

Chunsheng Feng

Date

02/27/2013

Modified by Chensong Zhang on 02/27/2013 for new FASP function names.

Definition at line 161 of file interface_mumps.c.

9.42 interface_samg.c File Reference

Interface to SAMG.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void dvector2SAMGInput (dvector *vec, char *filename)

Write a dvector to disk file in SAMG format (coordinate format)

INT dCSRmat2SAMGInput (dCSRmat *A, char *filefrm, char *fileamg)

Write SAMG Input data from a sparse matrix of CSR format.

9.42.1 Detailed Description

Interface to SAMG. Add reference for SAMG by K. Stuben here!

Definition in file interface_samg.c.

9.42.2 Function Documentation

9.42.2.1 INT dCSRmat2SAMGInput (dCSRmat * A, char * filefrm, char * fileamg)

Write SAMG Input data from a sparse matrix of CSR format.

Parameters

	*A	pointer to the dCSRmat matrix
Γ	*filefrm	pointer to the name of the .frm file
Г	*fileamg	pointer to the name of the .amg file

Author

Zhiyang Zhou

Date

2010/08/25

Definition at line 56 of file interface_samg.c.

9.42.2.2 void dvector2SAMGInput (dvector * vec, char * filename)

Write a dvector to disk file in SAMG format (coordinate format)

Parameters

* <i>Vec</i>	pointer to the dvector
*filename	char for vector file name

Author

Zhiyang Zhou

Date

08/25/2010

Definition at line 27 of file interface_samg.c.

9.43 interface_superlu.c File Reference

Interface to SuperLU direct solvers.

```
#include <stdio.h>
#include <stdlib.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

• int fasp_solver_superlu (dCSRmat *ptrA, dvector *b, dvector *u, const int print_level)

Solve Au=b by SuperLU.

9.43.1 Detailed Description

Interface to SuperLU direct solvers.

Definition in file interface_superlu.c.

9.43.2 Function Documentation

9.43.2.1 int fasp_solver_superlu (dCSRmat * ptrA, dvector * b, dvector * u, const int print_level)

Solve Au=b by SuperLU.

Parameters

ptrA	Pointer to a dCSRmat matrix
b	Pointer to the dvector of right-hand side term

и	Pointer to the dvector of solution
print_level	Output level

Author

Xiaozhe Hu

Date

11/05/09

Modified by Chensong Zhang on 11/01/2012 for new FASP function names. Modified by Chensong Zhang on 02/27/2013 for new FASP function names.

Definition at line 39 of file interface superlu.c.

9.44 interface_umfpack.c File Reference

Interface to UMFPACK direct solvers.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

• int fasp_solver_umfpack (dCSRmat *ptrA, dvector *b, dvector *u, const int print_level) Solve Au=b by UMFpack.

9.44.1 Detailed Description

Interface to UMFPACK direct solvers.

Definition in file interface_umfpack.c.

9.44.2 Function Documentation

```
9.44.2.1 int fasp_solver_umfpack ( dCSRmat * ptrA, dvector * b, dvector * u, const int print_level )
```

Solve Au=b by UMFpack.

Parameters

ptrA	Pointer to a dCSRmat matrix
b	Pointer to the dvector of right-hand side term
и	Pointer to the dvector of solution

print_level Output level

Author

Chensong Zhang

Date

05/20/2010

Modified by Chensong Zhang on 02/27/2013 for new FASP function names.

Definition at line 34 of file interface umfpack.c.

9.45 interpolation.c File Reference

Interpolation operators for AMG.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

- void fasp_amg_interp (dCSRmat *A, ivector *vertices, dCSRmat *P, iCSRmat *S, AMG_param *param)

 Generate interpolation operator P.
- void fasp_amg_interp1 (dCSRmat *A, ivector *vertices, dCSRmat *P, AMG_param *param, iCSRmat *S, INT *icor_ysk)

Generate interpolation operator P.

void fasp_amg_interp_trunc (dCSRmat *P, AMG_param *param)

Trunction step for prolongation operators.

9.45.1 Detailed Description

Interpolation operators for AMG.

Note

Ref U. Trottenberg, C. W. Oosterlee, and A. Schuller Multigrid (Appendix A: An Intro to Algebraic Multigrid) Academic Press Inc., San Diego, CA, 2001 With contributions by A. Brandt, P. Oswald and K. Stuben.

Definition in file interpolation.c.

9.45.2 Function Documentation

9.45.2.1 void fasp_amg_interp (dCSRmat * A, ivector * vertices, dCSRmat * P, iCSRmat * S, AMG_param * param)

Generate interpolation operator P.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix (index starts from 0)
vertices	Indicator vector for the C/F splitting of the variables
Р	Prolongation (input: nonzero pattern, output: prolongation)
S	Strong connection matrix
param	AMG parameters

Author

Xuehai Huang, Chensong Zhang

Date

04/04/2010

Modified by Xiaozhe Hu on 05/23/2012: add S as input Modified by Chensong Zhang on 09/12/2012: clean up and debug interp RS Modified by Chensong Zhang on 05/14/2013: reconstruct the code

Definition at line 48 of file interpolation.c.

9.45.2.2 void fasp_amg_interp1 (dCSRmat * A, ivector * vertices, dCSRmat * P, AMG_param * param, iCSRmat * S, INT * icor_ysk)

Generate interpolation operator P.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix (index starts from 0)
vertices	Indicator vector for the C/F splitting of the variables
Р	Prolongation (input: nonzero pattern, output: prolongation)
S	Strong connection matrix
param	AMG parameters
icor_ysk	Indices of coarse nodes in fine grid

Returns

SUCCESS or error message

Author

Chunsheng Feng, Xiaoqiang Yue

Date

03/01/2011

Modified by Chensong Zhang on 05/14/2013: reconstruct the code

Definition at line 105 of file interpolation.c.

9.45.2.3 void fasp_amg_interp_trunc (dCSRmat * P, $AMG_param * param$)

Trunction step for prolongation operators.

Parameters

Р	Prolongation (input: full, output: truncated)
param	Pointer to AMG_param: AMG parameters

Author

Chensong Zhang

Date

05/14/2013

Originally by Xuehai Huang, Chensong Zhang on 01/31/2009 Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012: add OMP support Modified by Chensong Zhang on 05/14/2013: rewritten

Definition at line 158 of file interpolation.c.

9.46 interpolation_em.c File Reference

Interpolation operators for AMG based on energy-min.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

• void fasp_amg_interp_em (dCSRmat *A, ivector *vertices, dCSRmat *P, AMG_param *param) Energy-min interpolation.

9.46.1 Detailed Description

Interpolation operators for AMG based on energy-min.

Note

Ref J. Xu and L. Zikatanov "On An Energy Minimazing Basis in Algebraic Multigrid Methods" Computing and visualization in sciences, 2003

Definition in file interpolation_em.c.

9.46.2 Function Documentation

9.46.2.1 void fasp_amg_interp_em (dCSRmat * A, ivector * vertices, dCSRmat * P, AMG_param * param)

Energy-min interpolation.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix (index starts from 0)
vertices	Pointer to the indicator of CF splitting on fine or coarse grid
Р	Pointer to the dCSRmat matrix of resulted interpolation
param	Pointer to AMG_param: AMG parameters

Author

Shuo Zhang, Xuehai Huang

Date

04/04/2010

Modified by Chunsheng Feng, Zheng Li on 10/17/2012: add OMP support Modified by Chensong Zhang on 05/14/2013: reconstruct the code

Definition at line 49 of file interpolation_em.c.

9.47 io.c File Reference

Matrix-vector input/output subroutines.

```
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

• void fasp_dcsrvec1_read (char *filename, dCSRmat *A, dvector *b)

Read A and b from a SINGLE disk file.

void fasp_dcsrvec2_read (char *filemat, char *filerhs, dCSRmat *A, dvector *b)

Read A and b from two disk files.

void fasp_dcsr_read (char *filename, dCSRmat *A)

Read A from matrix disk file in IJ format.

void fasp_dcoo_read (char *filename, dCSRmat *A)

Read A from matrix disk file in IJ format – indices starting from 0.

void fasp_dcoo1_read (char *filename, dCOOmat *A)

Read A from matrix disk file in IJ format – indices starting from 0.

void fasp_dmtx_read (char *filename, dCSRmat *A)

Read A from matrix disk file in MatrixMarket general format.

void fasp_dmtxsym_read (char *filename, dCSRmat *A)

Read A from matrix disk file in MatrixMarket sym format.

void fasp_dstr_read (char *filename, dSTRmat *A)

Read A from a disk file in dSTRmat format.

void fasp_dbsr_read (char *filename, dBSRmat *A)

Read A from a disk file in dBSRmat format.

void fasp dvecind read (char *filename, dvector *b)

Read b from matrix disk file. void fasp dvec read (char *filename, dvector *b) Read b from a disk file in array format. void fasp ivecind read (char *filename, ivector *b) Read b from matrix disk file. void fasp ivec read (char *filename, ivector *b) Read b from a disk file in array format. void fasp_dcsrvec1_write (char *filename, dCSRmat *A, dvector *b) Write A and b to a SINGLE disk file. void fasp dcsrvec2 write (char *filemat, char *filerhs, dCSRmat *A, dvector *b) Write A and b to two disk files. void fasp_dcoo_write (char *filename, dCSRmat *A) Write a matrix to disk file in IJ format (coordinate format) void fasp dstr write (char *filename, dSTRmat *A) Write a dSTRmat to a disk file. void fasp_dbsr_write (char *filename, dBSRmat *A) Write a dBSRmat to a disk file. void fasp_dvec_write (char *filename, dvector *vec) Write a dvector to disk file. void fasp_dvecind_write (char *filename, dvector *vec) Write a dvector to disk file in coordinate format. void fasp_ivec_write (char *filename, ivector *vec) Write a ivector to disk file in coordinate format. void fasp_dvec_print (INT n, dvector *u) Print first n entries of a vector of REAL type. void fasp_ivec_print (INT n, ivector *u) Print first n entries of a vector of INT type. void fasp_dcsr_print (dCSRmat *A) Print out a dCSRmat matrix in coordinate format. void fasp dcoo print (dCOOmat *A) Print out a dCOOmat matrix in coordinate format. void fasp_dbsr_print (dBSRmat *A) Print out a dBSRmat matrix in coordinate format. void fasp_dbsr_write_coo (const char *filename, const dBSRmat *A) Print out a dBSRmat matrix in coordinate format for matlab spy. void fasp_dcsr_write_coo (const char *filename, const dCSRmat *A) void fasp_dstr_print (dSTRmat *A) Print out a dSTRmat matrix in coordinate format. void fasp_matrix_read (char *filename, void *A) Read matrix from different kinds of formats from both ASCII and binary files. void fasp matrix read bin (char *filename, void *A) Read matrix in binary format. void fasp_matrix_write (char *filename, void *A, INT flag) write matrix from different kinds of formats from both ASCII and binary files void fasp vector read (char *filerhs, void *b)

Read RHS vector from different kinds of formats from both ASCII and binary files.

write RHS vector from different kinds of formats in both ASCII and binary files

void fasp vector write (char *filerhs, void *b, INT flag)

Variables

· INT ilength

Flags which indicates lengths of INT and REAL numbers.

INT dlength

9.47.1 Detailed Description

Matrix-vector input/output subroutines.

Note

Read, write or print a matrix or a vector in various formats.

Definition in file io.c.

9.47.2 Function Documentation

9.47.2.1 void fasp_dbsr_print (dBSRmat * A)

Print out a dBSRmat matrix in coordinate format.

Parameters

A Pointer to the dBSRmat matrix A

Author

Ziteng Wang

Date

12/24/2012

Modified by Chunsheng Feng

Date

11/16/2013

Definition at line 1384 of file io.c.

9.47.2.2 void fasp_dbsr_read (char * filename, dBSRmat * A)

Read A from a disk file in dBSRmat format.

Parameters

filename	File name for matrix A
Α	Pointer to the dBSRmat A

Note

This routine reads a dBSRmat matrix from a disk file in the following format:

File format:

- · ROW, COL, NNZ
- · nb: size of each block
- · storage_manner: storage manner of each block
- · ROW+1: length of IA
- IA(i), i=0:ROW
- · NNZ: length of JA
- JA(i), i=0:NNZ-1
- NNZ*nb*nb: length of val
- val(i), i=0:NNZ*nb*nb-1

Author

Xiaozhe Hu

Date

10/29/2010

Definition at line 635 of file io.c.

9.47.2.3 void fasp_dbsr_write (char * filename, dBSRmat * A)

Write a dBSRmat to a disk file.

Parameters

filename	File name for A
Α	Pointer to the dBSRmat matrix A

Note

The routine writes the specified REAL vector in BSR format. Refer to the reading subroutine $\route{mathemath{\mathsf{Ne}}}$

Author

Shiquan Zhang

Date

10/29/2010

Definition at line 1143 of file io.c.

9.47.2.4 void fasp_dbsr_write_coo (const char * filename, const dBSRmat * A)

Print out a dBSRmat matrix in coordinate format for matlab spy.

Parameters

A Pointer to the dBSRmat matrix A

Author

Chunsheng Feng

Date

11/14/2013

Definition at line 1418 of file io.c.

9.47.2.5 void fasp_dcoo1_read (char * filename, dCOOmat * A)

Read A from matrix disk file in IJ format - indices starting from 0.

Parameters

ilename	File name for matrix
Α	Pointer to the COO matrix

Note

File format:

- nrow ncol nnz % number of rows, number of columns, and nnz
- i j a_ij % i, j a_ij in each line

difference between fasp dooo read and this function is this function do not change to CSR format

Author

Xiaozhe Hu

Date

03/24/2013

Definition at line 366 of file io.c.

9.47.2.6 void fasp_dcoo_print (dCOOmat * A)

Print out a dCOOmat matrix in coordinate format.

Parameters

Α	Pointer to the dCOOmat matrix A
---	---------------------------------

Author

Ziteng Wang

Date

12/24/2012

Definition at line 1362 of file io.c.

```
9.47.2.7 void fasp_dcoo_read ( char * filename, dCSRmat * A )
```

Read A from matrix disk file in IJ format - indices starting from 0.

Parameters

filename	File name for matrix
Α	Pointer to the CSR matrix

Note

File format:

- nrow ncol nnz % number of rows, number of columns, and nnz
- i j a_ij % i, j a_ij in each line

After reading, it converts the matrix to dCSRmat format.

Author

Xuehai Huang, Chensong Zhang

Date

03/29/2009

Definition at line 315 of file io.c.

```
9.47.2.8 void fasp_dcoo_write ( char * filename, dCSRmat * A )
```

Write a matrix to disk file in IJ format (coordinate format)

Parameters

Α	pointer to the dCSRmat matrix
filename	char for vector file name

Note

```
The routine writes the specified REAL vector in COO format. Refer to the reading subroutine \r fasp_dcoo_read.
```

File format:

- The first line of the file gives the number of rows, the number of columns, and the number of nonzeros.
- Then gives nonzero values in i j a(i,j) format.

Author

Chensong Zhang

Date

03/29/2009

Definition at line 1043 of file io.c.

9.47.2.9 void fasp_dcsr_print (dCSRmat * A)

Print out a dCSRmat matrix in coordinate format.

Parameters

A	Pointer to the dCSRmat matrix A

Author

Xuehai Huang

Date

03/29/2009

Definition at line 1340 of file io.c.

9.47.2.10 void fasp_dcsr_read (char * filename, dCSRmat * A)

Read A from matrix disk file in IJ format.

Parameters

*filename	char for matrix file name
* A	pointer to the CSR matrix

Author

Ziteng Wang

Date

12/25/2012

Definition at line 254 of file io.c.

9.47.2.11 void fasp_dcsrvec1_read (char * filename, dCSRmat * A, dvector * b)

Read A and b from a SINGLE disk file.

Parameters

ſ	filename	File name
ĺ	Α	Pointer to the CSR matrix
	b	Pointer to the dvector

Note

This routine reads a dCSRmat matrix and a dvector vector from a single disk file.

The difference between this and fasp_dcoovec_read is that this routine support non-square matrices.

File format:

- nrow ncol % number of rows and number of columns
- ia(j), j=0:nrow % row index
- ja(j), j=0:nnz-1 % column index

- a(j), j=0:nnz-1 % entry value
- n % number of entries
- b(j), j=0:n-1 % entry value

Author

Xuehai Huang

Date

03/29/2009

Modified by Chensong Zhang on 03/14/2012

Definition at line 84 of file io.c.

9.47.2.12 void fasp_dcsrvec1_write (char * filename, dCSRmat * A, dvector * b)

Write A and b to a SINGLE disk file.

Parameters

filename	File name
Α	Pointer to the CSR matrix
b	Pointer to the dvector

Note

This routine writes a dCSRmat matrix and a dvector vector to a single disk file. File format:

- nrow ncol % number of rows and number of columns
- ia(j), j=0:nrow % row index
- ja(j), j=0:nnz-1 % column index
- a(j), j=0:nnz-1 % entry value
- n % number of entries
- b(j), j=0:n-1 % entry value

Author

Feiteng Huang

Date

05/19/2012

Modified by Chensong on 12/26/2012

Definition at line 895 of file io.c.

9.47.2.13 void fasp_dcsrvec2_read (char * filemat, char * filerhs, dCSRmat * A, dvector * b)

Read A and b from two disk files.

Parameters

filemat	File name for matrix
filerhs	File name for right-hand side
Α	Pointer to the dCSR matrix
b	Pointer to the dvector

Note

This routine reads a dCSRmat matrix and a dvector vector from a disk file.

CSR matrix file format:

- nrow % number of columns (rows)
- ia(j), j=0:nrow % row index
- ja(j), j=0:nnz-1 % column index
- a(j), j=0:nnz-1 % entry value

RHS file format:

- n % number of entries
- b(j), j=0:nrow-1 % entry value

Indices start from 1, NOT 0!!!

Author

Zhiyang Zhou

Date

2010/08/06

Modified by Chensong Zhang on 2011/03/01 Modified by Chensong Zhang on 2012/01/05 Definition at line 175 of file io.c.

9.47.2.14 void fasp_dcsrvec2_write (char * filemat, char * filerhs, dCSRmat * A, dvector * b)

Write A and b to two disk files.

Parameters

filemat	File name for matrix
filerhs	File name for right-hand side
Α	Pointer to the dCSR matrix
b	Pointer to the dvector

Note

This routine writes a dCSRmat matrix and a dvector vector to two disk files.

CSR matrix file format:

- nrow % number of columns (rows)
- ia(j), j=0:nrow % row index
- ja(j), j=0:nnz-1 % column index
- a(j), j=0:nnz-1 % entry value

RHS file format:

- n % number of entries
- b(j), j=0:nrow-1 % entry value

Indices start from 1, NOT 0!!!

Author

Feiteng Huang

Date

05/19/2012

Definition at line 972 of file io.c.

9.47.2.15 void fasp_dmtx_read (char * filename, dCSRmat * A)

Read A from matrix disk file in MatrixMarket general format.

Parameters

filename	File name for matrix
Α	Pointer to the CSR matrix

Note

File format: This routine reads a MatrixMarket general matrix from a mtx file. And it converts the matrix to dCS-Rmat format. For details of mtx format, please refer to http://math.nist.gov/MatrixMarket/. Indices start from 1, NOT 0!!!

Author

Chensong Zhang

Date

09/05/2011

Definition at line 416 of file io.c.

9.47.2.16 void fasp_dmtxsym_read (char * filename, dCSRmat * A)

Read A from matrix disk file in MatrixMarket sym format.

Parameters

filename	File name for matrix
----------	----------------------

Note

File format: This routine reads a MatrixMarket symmetric matrix from a mtx file. And it converts the matrix to dCSRmat format. For details of mtx format, please refer to http://math.nist.gov/MatrixMarket/.

```
Indices start from 1, NOT 0!!!
```

Author

Chensong Zhang

Date

09/02/2011

Definition at line 478 of file io.c.

```
9.47.2.17 void fasp_dstr_print ( dSTRmat * A )
```

Print out a dSTRmat matrix in coordinate format.

Parameters

Α	Pointer to the dSTRmat matrix A
---	---------------------------------

Author

Ziteng Wang

Date

12/24/2012

Definition at line 1499 of file io.c.

9.47.2.18 void fasp_dstr_read (char * filename, dSTRmat * A)

Read A from a disk file in dSTRmat format.

Parameters

filename	File name for the matrix
Α	Pointer to the dSTRmat

Note

This routine reads a dSTRmat matrix from a disk file. After done, it converts the matrix to dCSRmat format. File format:

- nx, ny, nz
- · nc: number of components
- · nband: number of bands

- n: size of diagonal, you must have diagonal
- diag(j), j=0:n-1
- offset, length: offset and length of off-diag1
- offdiag(j), j=0:length-1

Author

Xuehai Huang

Date

03/29/2009

Definition at line 555 of file io.c.

9.47.2.19 void fasp_dstr_write (char * filename, dSTRmat * A)

Write a dSTRmat to a disk file.

Parameters

filename	File name for A
Α	Pointer to the dSTRmat matrix A

Note

The routine writes the specified REAL vector in STR format. Refer to the reading subroutine \ref fasp_dstr_read.

Author

Shiquan Zhang

Date

03/29/2010

Definition at line 1083 of file io.c.

9.47.2.20 void fasp_dvec_print (INT n, dvector * u)

Print first n entries of a vector of REAL type.

Parameters

n	An interger (if n=0, then print all entries)
и	Pointer to a dvector

Author

Chensong Zhang

Date

03/29/2009

Definition at line 1301 of file io.c.

```
9.47.2.21 void fasp_dvec_read ( char * filename, dvector * b )
```

Read b from a disk file in array format.

Parameters

filename	File name for vector b
b	Pointer to the dvector b (output)

Note

File Format:

- nrow
- val_j, j=0:nrow-1

Author

Chensong Zhang

Date

03/29/2009

Definition at line 754 of file io.c.

9.47.2.22 void fasp_dvec_write (char * filename, dvector * vec)

Write a dvector to disk file.

Parameters

vec	Pointer to the dvector
filename	File name

Author

Xuehai Huang

Date

03/29/2009

Definition at line 1198 of file io.c.

9.47.2.23 void fasp_dvecind_read (char * filename, dvector * b)

Read b from matrix disk file.

Parameters

filename	File name for vector b
b	Pointer to the dvector b (output)

Note

File Format:

- nrow
- ind_j, val_j, j=0:nrow-1

Because the index is given, order is not important!

Author

Chensong Zhang

Date

03/29/2009

Definition at line 704 of file io.c.

9.47.2.24 void fasp_dvecind_write (char * filename, dvector * vec)

Write a dvector to disk file in coordinate format.

Parameters

vec	Pointer to the dvector
filename	File name

Note

The routine writes the specified REAL vector in IJ format.

- The first line of the file is the length of the vector;
- · After that, each line gives index and value of the entries.

Author

Xuehai Huang

Date

03/29/2009

Definition at line 1234 of file io.c.

9.47.2.25 void fasp_ivec_print (INT n, ivector *u)

Print first n entries of a vector of INT type.

Parameters

n	An interger (if n=0, then print all entries)
и	Pointer to an ivector

Author

Chensong Zhang

Date

03/29/2009

Definition at line 1321 of file io.c.

9.47.2.26 void fasp_ivec_read (char * filename, ivector * b)

Read b from a disk file in array format.

Parameters

filename	File name for vector b
b	Pointer to the dvector b (output)

Note

File Format:

- nrow
- val_j, j=0:nrow-1

Author

Xuehai Huang

Date

03/29/2009

Definition at line 844 of file io.c.

9.47.2.27 void fasp_ivec_write (char * filename, ivector * vec)

Write a ivector to disk file in coordinate format.

Parameters

vec	Pointer to the dvector
filename	File name

Note

The routine writes the specified INT vector in IJ format.

- The first line of the file is the length of the vector;
- · After that, each line gives index and value of the entries.

Author

Xuehai Huang

Date

03/29/2009

Definition at line 1269 of file io.c.

9.47.2.28 void fasp_ivecind_read (char * filename, ivector * b)

Read b from matrix disk file.

Parameters

filename	File name for vector b
b	Pointer to the dvector b (output)

Note

File Format:

- nrow
- ind_j, val_j ... j=0:nrow-1

Author

Chensong Zhang

Date

03/29/2009

Definition at line 804 of file io.c.

9.47.2.29 fasp_matrix_read (char * filemat, void * A)

Read matrix from different kinds of formats from both ASCII and binary files.

Parameters

filemat

A Pointer to the matr

Note

Flags for matrix file format:

- fileflag % fileflag = 1: binary, fileflag = 0000: ASCII
- formatflag % a 3-digit number for internal use, see below
- · matrix % different types of matrix

Meaning of formatflag:

- · matrixflag % first digit of formatflag
 - matrixflag = 1: CSR format
 - matrixflag = 2: BSR format
 - matrixflag = 3: STR format
 - matrixflag = 4: COO format
 - matrixflag = 5: MTX format
 - matrixflag = 6: MTX symmetrical format
- · ilength % third digit of formatflag, length of INT
- · dlength % fourth digit of formatflag, length of REAL

Author

Ziteng Wang

Date

12/24/2012

Modified by Chensong Zhang on 05/01/2013

Definition at line 1533 of file io.c.

9.47.2.30 void fasp_matrix_read_bin (char * filemat, void * A)

Read matrix in binary format.

Parameters

filemat	File name of matrix file
Α	Pointer to the matrix

Author

Xiaozhe Hu

Date

04/14/2013

Modified by Chensong Zhang on 05/01/2013: Use it to read binary files!!!

Definition at line 1638 of file io.c.

9.47.2.31 fasp_matrix_write (char * filemat, void * A, INT flag)

write matrix from different kinds of formats from both ASCII and binary files

Parameters

filemat	File name of matrix file
Α	Pointer to the matrix
flag	Type of file and matrix, a 3-digit number

Note

Meaning of flag:

- fileflag % fileflag = 1: binary, fileflag = 0: ASCII
- · matrixflag
 - matrixflag = 1: CSR format
 - matrixflag = 2: BSR format
 - matrixflag = 3: STR format

Matrix file format:

- fileflag % fileflag = 1: binary, fileflag = 0000: ASCII
- formatflag % a 3-digit number
- · matrixflag % different kinds of matrix judged by formatflag

Author

Ziteng Wang

Date

12/24/2012

Definition at line 1712 of file io.c.

9.47.2.32 fasp_vector_read (char * filerhs, void * b)

Read RHS vector from different kinds of formats from both ASCII and binary files.

Parameters

filerhs	File name of vector file
b	Pointer to the vector

Note

Matrix file format:

- fileflag % fileflag = 1: binary, fileflag = 0000: ASCII
- formatflag % a 3-digit number
- · vector % different kinds of vector judged by formatflag

Meaning of formatflag:

- · vectorflag % first digit of formatflag
 - vectorflag = 1: dvec format
 - vectorflag = 2: ivec format
 - vectorflag = 3: dvecind format

- vectorflag = 4: ivecind format
- ilength % second digit of formatflag, length of INT
- · dlength % third digit of formatflag, length of REAL

Author

Ziteng Wang

Date

12/24/2012

Definition at line 1805 of file io.c.

9.47.2.33 fasp_vector_write (char * filerhs, void * b, INT flag)

write RHS vector from different kinds of formats in both ASCII and binary files

Parameters

filerhs	File name of vector file
b	Pointer to the vector
flag	Type of file and vector, a 2-digit number

Note

Meaning of the flags

- fileflag % fileflag = 1: binary, fileflag = 0: ASCII
- · vectorflag
 - vectorflag = 1: dvec format
 - vectorflag = 2: ivec format
 - vectorflag = 3: dvecind format
 - vectorflag = 4: ivecind format

Matrix file format:

- fileflag % fileflag = 1: binary, fileflag = 0000: ASCII
- formatflag % a 2-digit number
- · vectorflag % different kinds of vector judged by formatflag

Author

Ziteng Wang

Date

12/24/2012

Modified by Chensong Zhang on 05/02/2013: fix a bug when writing in binary format Definition at line 1902 of file io.c.

9.48 itsolver_bcsr.c File Reference

Iterative solvers for block_dCSRmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_block.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

• INT fasp_solver_bdcsr_itsolver (block_dCSRmat *A, dvector *b, dvector *x, precond *pc, itsolver_param *itparam)

Solve Ax = b by standard Krylov methods.

• INT fasp_solver_bdcsr_krylov (block_dCSRmat *A, dvector *b, dvector *x, itsolver_param *itparam) Solve Ax = b by standard Krylov methods.

9.48.1 Detailed Description

Iterative solvers for block_dCSRmat matrices.

Definition in file itsolver_bcsr.c.

9.48.2 Function Documentation

9.48.2.1 INT fasp_solver_bdcsr_itsolver (block_dCSRmat * A, dvector * b, dvector * x, precond * pc, itsolver_param * itparam)

Solve Ax = b by standard Krylov methods.

Parameters

Α	Pointer to the coeff matrix in block_dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
рс	Pointer to the preconditioning action
itparam	Pointer to parameters for iterative solvers

Returns

Number of iterations if succeed

Author

Chensong Zhang

Date

11/25/2010

Definition at line 35 of file itsolver bcsr.c.

9.48.2.2 INT fasp_solver_bdcsr_krylov (block_dCSRmat * A, dvector * b, dvector * x, itsolver_param * itparam)

Solve Ax = b by standard Krylov methods.

Parameters

Α	Pointer to the coeff matrix in block_dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

Returns

Number of iterations if succeed

Author

Xiaozhe Hu

Date

07/18/2010

Definition at line 105 of file itsolver_bcsr.c.

9.49 itsolver_bsr.c File Reference

Iterative solvers for dBSRmat matrices.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

void fasp_set_GS_threads (INT mythreads, INT its)

Set threads for CPR. Please add it at the begin of Krylov openmp method function and after iter++.

- INT fasp_solver_dbsr_itsolver (dBSRmat *A, dvector *b, dvector *x, precond *pc, itsolver_param *itparam)

 Solve Ax=b by preconditioned Krylov methods for BSR matrices.
- INT fasp_solver_dbsr_krylov (dBSRmat *A, dvector *b, dvector *x, itsolver_param *itparam)

Solve Ax=b by standard Krylov methods for BSR matrices.

INT fasp_solver_dbsr_krylov_diag (dBSRmat *A, dvector *b, dvector *x, itsolver_param *itparam)

Solve Ax=b by diagonal preconditioned Krylov methods.

• INT fasp_solver_dbsr_krylov_ilu (dBSRmat *A, dvector *b, dvector *x, itsolver_param *itparam, ILU_param *iluparam)

Solve Ax=b by ILUs preconditioned Krylov methods.

• INT fasp_solver_dbsr_krylov_amg (dBSRmat *A, dvector *b, dvector *x, itsolver_param *itparam, AMG_param *amgparam)

Solve Ax=b by AMG preconditioned Krylov methods.

Variables

- INT THDs_AMG_GS =0
- INT THDs_CPR_IGS =0
- INT THDs_CPR_gGS =0

9.49.1 Detailed Description

Iterative solvers for dBSRmat matrices.

Definition in file itsolver_bsr.c.

9.49.2 Function Documentation

9.49.2.1 void fasp_set_GS_threads (INT threads, INT its)

Set threads for CPR. Please add it at the begin of Krylov openmp method function and after iter++.

Parameters

threads	Total threads of sovler
its	Current its of the Krylov methods

Author

Feng Chunsheng, Yue Xiaoqiang

Date

03/20/2011

TODO: Why put it here??? - Chensong

Definition at line 39 of file itsolver_bsr.c.

9.49.2.2 INT fasp_solver_dbsr_itsolver (dBSRmat * A, dvector * b, dvector * x, precond * pc, itsolver_param * itparam)

Solve Ax=b by preconditioned Krylov methods for BSR matrices.

Parameters

Α	Pointer to the coeff matrix in dBSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
рс	Pointer to the preconditioning action
itparam	Pointer to parameters for iterative solvers

Returns

Number of iterations if succeed

Author

Zhiyang Zhou, Xiaozhe Hu

Date

10/26/2010

Definition at line 100 of file itsolver_bsr.c.

9.49.2.3 INT fasp_solver_dbsr_krylov (dBSRmat * A, dvector * b, dvector * x, $itsolver_param * itparam$)

Solve Ax=b by standard Krylov methods for BSR matrices.

Parameters

Α	Pointer to the coeff matrix in dBSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

Returns

Number of iterations if succeed

Author

Zhiyang Zhou, Xiaozhe Hu

Date

10/26/2010

Definition at line 175 of file itsolver_bsr.c.

9.49.2.4 INT fasp_solver_dbsr_krylov_amg (dBSRmat * A, dvector * b, dvector * x, itsolver_param * itparam, AMG_param * amgparam)

Solve Ax=b by AMG preconditioned Krylov methods.

Parameters

Α	Pointer to the coeff matrix in dBSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
amgparam	Pointer to parameters of AMG

Returns

Number of iterations if succeed

Author

Xiaozhe Hu

Date

03/16/2012

parameters of iterative method

Definition at line 382 of file itsolver_bsr.c.

9.49.2.5 INT fasp_solver_dbsr_krylov_diag (dBSRmat * A, dvector * b, dvector * x, itsolver_param * itparam)

Solve Ax=b by diagonal preconditioned Krylov methods.

Parameters

Α	Pointer to the coeff matrix in dBSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

Returns

the number of iterations

Author

Zhiyang Zhou, Xiaozhe Hu

Date

10/26/2010

Modified by Chunsheng Feng, Zheng Li

Date

10/15/2012

Definition at line 219 of file itsolver_bsr.c.

9.49.2.6 INT fasp_solver_dbsr_krylov_ilu (dBSRmat * A, dvector * b, dvector * x, itsolver_param * itparam, ILU_param * iluparam)

Solve Ax=b by ILUs preconditioned Krylov methods.

Parameters

Α	Pointer to the coeff matrix in dBSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
iluparam	Pointer to parameters of ILU

Returns

Number of iterations if succeed

Author

Shiquang Zhang, Xiaozhe Hu

Date

10/26/2010

Definition at line 315 of file itsolver_bsr.c.

9.49.3 Variable Documentation

9.49.3.1 INT THDs_AMG_GS =0

cpr amg gs smoothing threads

Definition at line 35 of file itsolver_bsr.c.

```
9.49.3.2 INT THDs_CPR_gGS =0
```

global matrix gs smoothing threads

Definition at line 37 of file itsolver_bsr.c.

```
9.49.3.3 INT THDs_CPR_IGS =0
```

reservoir gs smoothing threads

Definition at line 36 of file itsolver_bsr.c.

9.50 itsolver_csr.c File Reference

Iterative solvers for dCSRmat matrices.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

• INT fasp_solver_dcsr_itsolver (dCSRmat *A, dvector *b, dvector *x, precond *pc, itsolver_param *itparam)

Solve Ax=b by preconditioned Krylov methods for CSR matrices.

• INT fasp_solver_dcsr_krylov (dCSRmat *A, dvector *b, dvector *x, itsolver_param *itparam)

Solve Ax=b by standard Krylov methods for CSR matrices.

INT fasp_solver_dcsr_krylov_diag (dCSRmat *A, dvector *b, dvector *x, itsolver_param *itparam)

Solve Ax=b by diagonal preconditioned Krylov methods.

 INT fasp_solver_dcsr_krylov_schwarz (dCSRmat *A, dvector *b, dvector *x, itsolver_param *itparam, Schwarz-_param *schparam)

Solve Ax=b by overlapping schwarz Krylov methods.

INT fasp_solver_dcsr_krylov_amg (dCSRmat *A, dvector *b, dvector *x, itsolver_param *itparam, AMG_param *amgparam)

Solve Ax=b by AMG preconditioned Krylov methods.

• INT fasp_solver_dcsr_krylov_ilu (dCSRmat *A, dvector *b, dvector *x, itsolver_param *itparam, ILU_param *iluparam)

Solve Ax=b by ILUs preconditioned Krylov methods.

• INT fasp_solver_dcsr_krylov_ilu_M (dCSRmat *A, dvector *b, dvector *x, itsolver_param *itparam, ILU_param *iluparam, dCSRmat *M)

Solve Ax=b by ILUs preconditioned Krylov methods: ILU of M as preconditioner.

9.50.1 Detailed Description

Iterative solvers for dCSRmat matrices.

Definition in file itsolver_csr.c.

9.50.2 Function Documentation

9.50.2.1 INT fasp_solver_dcsr_itsolver (dCSRmat * A, dvector * b, dvector * x, precond * pc, itsolver_param * itparam)

Solve Ax=b by preconditioned Krylov methods for CSR matrices.

Parameters

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
рс	Pointer to the preconditioning action
itparam	Pointer to parameters for iterative solvers

Returns

Number of iterations if succeed

Author

Chensong Zhang

Date

09/25/2009

Note

This is an abstract interface for iterative methods.

Definition at line 39 of file itsolver_csr.c.

9.50.2.2 INT fasp_solver_dcsr_krylov (dCSRmat * A, dvector * b, dvector * x, itsolver_param * itparam)

Solve Ax=b by standard Krylov methods for CSR matrices.

Parameters

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
Х	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

Returns

Number of iterations if succeed

Author

Chensong Zhang, Shiquan Zhang

Date

09/25/2009

Definition at line 139 of file itsolver_csr.c.

9.50.2.3 INT fasp_solver_dcsr_krylov_amg (dCSRmat * A, dvector * b, dvector * x, itsolver_param * itparam, AMG_param * amgparam)

Solve Ax=b by AMG preconditioned Krylov methods.

Parameters

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
amgparam	Pointer to parameters for AMG methods

Returns

Number of iterations if succeed

Author

Chensong Zhang

Date

09/25/2009

Definition at line 330 of file itsolver_csr.c.

9.50.2.4 INT fasp_solver_dcsr_krylov_diag (dCSRmat * A, dvector * b, dvector * x, itsolver_param * itparam)

Solve Ax=b by diagonal preconditioned Krylov methods.

Parameters

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

Returns

Number of iterations if succeed

Author

Chensong Zhang, Shiquan Zhang

Date

09/25/2009

Definition at line 189 of file itsolver_csr.c.

9.50.2.5 INT fasp_solver_dcsr_krylov_ilu (dCSRmat * A, dvector * b, dvector * x, itsolver_param * itparam, ILU_param * iluparam)

Solve Ax=b by ILUs preconditioned Krylov methods.

Parameters

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
Х	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
iluparam	Pointer to parameters for ILU

Returns

Number of iterations if succeed

Author

Chensong Zhang, Shiquan Zhang

Date

09/25/2009

Definition at line 438 of file itsolver_csr.c.

9.50.2.6 INT fasp_solver_dcsr_krylov_ilu_M (dCSRmat * A, dvector * b, dvector * x, itsolver_param * itparam, ILU_param * iluparam, dCSRmat * M)

Solve Ax=b by ILUs preconditioned Krylov methods: ILU of M as preconditioner.

Parameters

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
iluparam	Pointer to parameters for ILU
М	Pointer to the preconditioning matrix in dCSRmat format

Returns

Number of iterations if succeed

Author

Xiaozhe Hu

Date

09/25/2009

Note

This function is specially designed for reservoir simulation. Have not been tested in any other places.

Definition at line 525 of file itsolver_csr.c.

9.50.2.7 INT fasp_solver_dcsr_krylov_schwarz (dCSRmat * A, dvector * b, dvector * x, itsolver_param * itparam, Schwarz_param * schparam)

Solve Ax=b by overlapping schwarz Krylov methods.

Parameters

Α	Pointer to the coeff matrix in dCSRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
schparam	Pointer to parameters for Schwarz methods

Returns

Number of iterations

Author

Xiaozhe Hu

Date

03/21/2011

Modified by Chensong on 07/02/2012: change interface

Definition at line 253 of file itsolver_csr.c.

9.51 itsolver_mf.c File Reference

Iterative solvers with matrix-free spmv.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "fasp_block.h"
#include "itsolver_util.inl"
```

Functions

- INT fasp_solver_itsolver (mxv_matfree *mf, dvector *b, dvector *x, precond *pc, itsolver_param *itparam)

 Solve Ax=b by preconditioned Krylov methods for CSR matrices.
- INT fasp_solver_krylov (mxv_matfree *mf, dvector *b, dvector *x, itsolver_param *itparam)

Solve Ax=b by standard Krylov methods – without preconditioner.

void fasp_solver_itsolver_init (INT matrix_format, mxv_matfree *mf, void *A)
 Initialize itsovlers.

9.51.1 Detailed Description

Iterative solvers with matrix-free spmv.

Definition in file itsolver_mf.c.

9.51.2 Function Documentation

9.51.2.1 INT fasp_solver_itsolver ($mxv_matfree*mf$, dvector*b, dvector*x, precond*pc, $itsolver_param*itparam$)

Solve Ax=b by preconditioned Krylov methods for CSR matrices.

Parameters

mf	Pointer to mxv_matfree matrix-free spmv operation
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
рс	Pointer to the preconditioning action
itparam	Pointer to parameters for iterative solvers

Returns

Number of iterations if succeed

Author

Chensong Zhang

Date

09/25/2009

Note

This is an abstract interface for iterative methods.

Modified by Feiteng Huang on 09/19/2012: matrix free

Definition at line 50 of file itsolver_mf.c.

9.51.2.2 void fasp_solver_itsolver_init (INT matrix_format, mxv_matfree * mf, void * A)

Initialize itsovlers.

Parameters

matrix_format	matrix format
mf	Pointer to mxv_matfree matrix-free spmv operation
Α	void pointer to matrix

Author

Feiteng Huang

Date

09/18/2012

Modified by Chensong Zhang on 05/10/2013: Change interface of mat-free mv Definition at line 199 of file itsolver_mf.c.

9.51.2.3 INT fasp_solver_krylov (mxv_matfree * mf, dvector * b, dvector * x, itsolver_param * itparam)

Solve Ax=b by standard Krylov methods – without preconditioner.

Parameters

mf	Pointer to mxv_matfree matrix-free spmv operation
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

Returns

Number of iterations if succeed

Author

Chensong Zhang, Shiquan Zhang

Date

09/25/2009

Modified by Feiteng Huang on 09/20/2012: matrix free

Definition at line 151 of file itsolver_mf.c.

9.52 itsolver str.c File Reference

Iterative solvers for dSTRmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver util.inl"
```

Functions

- INT fasp_solver_dstr_itsolver (dSTRmat *A, dvector *b, dvector *x, precond *pc, itsolver_param *itparam)

 Solve Ax=b by standard Krylov methods.
- INT fasp_solver_dstr_krylov (dSTRmat *A, dvector *b, dvector *x, itsolver_param *itparam)

Solve Ax=b by standard Krylov methods.

- INT fasp_solver_dstr_krylov_diag (dSTRmat *A, dvector *b, dvector *x, itsolver_param *itparam)
- INT fasp_solver_dstr_krylov_ilu (dSTRmat *A, dvector *b, dvector *x, itsolver_param *itparam, ILU_param *iluparam)

Solve Ax=b by structured ILU preconditioned Krylov methods.

• INT fasp_solver_dstr_krylov_blockgs (dSTRmat *A, dvector *b, dvector *x, itsolver_param *itparam, ivector *neigh, ivector *order)

Solve Ax=b by diagonal preconditioned Krylov methods.

Solve Ax=b by diagonal preconditioned Krylov methods.

9.52.1 Detailed Description

Iterative solvers for dSTRmat matrices.

Definition in file itsolver_str.c.

9.52.2 Function Documentation

9.52.2.1 INT fasp_solver_dstr_itsolver (dSTRmat * A, dvector * b, dvector * x, precond * pc, itsolver_param * itparam)

Solve Ax=b by standard Krylov methods.

Parameters

Α	Pointer to the coeff matrix in dSTRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
рс	Pointer to the preconditioning action
itparam	Pointer to parameters for iterative solvers

Returns

Number of iterations if succeed

Author

Chensong Zhang

Date

09/25/2009

Definition at line 34 of file itsolver_str.c.

9.52.2.2 INT fasp_solver_dstr_krylov (dSTRmat * A, dvector * b, dvector * x, $itsolver_param * itparam$)

Solve Ax=b by standard Krylov methods.

Parameters

	Pointer to the coeff matrix in dSTRmat format
	Pointer to the right hand side in dvector format
	Pointer to the approx solution in dvector format
itparaı	Pointer to parameters for iterative solvers

Returns

Number of iterations if succeed

Author

Zhiyang Zhou

Date

04/25/2010

Definition at line 109 of file itsolver_str.c.

9.52.2.3 INT fasp_solver_dstr_krylov_blockgs (dSTRmat * A, dvector * b, dvector * x, itsolver_param * itparam, ivector * neigh, ivector * order)

Solve Ax=b by diagonal preconditioned Krylov methods.

Parameters

Α	Pointer to the coeff matrix in dSTRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
neigh	Pointer to neighbor vector
order	Pointer to solver ordering

Returns

Number of iterations if succeed

Author

Xiaozhe Hu

Date

10/10/2010

Definition at line 290 of file itsolver_str.c.

9.52.2.4 INT fasp_solver_dstr_krylov_diag (dSTRmat * A, dvector * b, dvector * x, itsolver_param * itparam)

Solve Ax=b by diagonal preconditioned Krylov methods.

Parameters

Α	Pointer to the coeff matrix in dSTRmat format
b	Pointer to the right hand side in dvector format
Χ	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers

Returns

Number of iterations if succeed

Author

Zhiyang Zhou

Date

4/23/2010

Definition at line 149 of file itsolver_str.c.

9.52.2.5 INT fasp_solver_dstr_krylov_ilu (dSTRmat * A, dvector * b, dvector * x, itsolver_param * itparam, ILU param * iluparam)

Solve Ax=b by structured ILU preconditioned Krylov methods.

Parameters

Α	Pointer to the coeff matrix in dSTRmat format
b	Pointer to the right hand side in dvector format
X	Pointer to the approx solution in dvector format
itparam	Pointer to parameters for iterative solvers
iluparam	Pointer to parameters for ILU

Returns

Number of iterations if succeed

Author

Xiaozhe Hu

Date

05/01/2010

Definition at line 207 of file itsolver_str.c.

9.53 itsolver util.inl File Reference

Routines for iterative solvers.

Macros

- #define ITS_FACONV printf("### WARNING: False convergence!\n")
 Warning for residual false convergence.
- #define ITS_ZEROSOL printf("### WARNING: Iteration stopped due to the solution is close to zero!\n")

 Warning for solution close to zero.
- #define ITS_RESTART printf("### WARNING: Iteration restarted due to stagnation!\n")

Warning for iteration restarted.

- #define ITS_STAGGED printf("### WARNING: Iteration stopped due to staggnation!\n")
 Warning for stagged iteration.
- #define ITS_ZEROTOL printf("### WARNING: The tolerence might be too small!\n")
- #define ITS DIVZERO printf("### WARNING: Divided by zero!\n")

Warning for tolerance practically close to zero.

Warning for divided by zero.

- #define ITS_REALRES(relres) printf("### WARNING: The actual relative residual = %e!\n",(relres)) Warning for actual relative residual.
- #define ITS_COMPRES(relres) printf("### WARNING: The computed relative residual = %e!\n",(relres))
 Warning for computed relative residual.

```
• #define ITS_SMALLSP printf("### WARNING: The sp is too small!\n") Warning for too small sp.
```

#define ITS_RESTORE(iter) printf("### WARNING: Restore iteration %d!!!",(iter));

Warning for restore previous iteration.

• #define ITS_DIFFRES(reldiff, relres) printf("||u-u'|| = %e and the comp. rel. res. = %e.\n",(reldiff),(relres));

Output relative difference and residual.

• #define ITS_PUTNORM(name, value) printf("L2 norm of %s = %e.\n",(name),(value));

Output L2 norm of some variable.

9.53.1 Detailed Description

Routines for iterative solvers.

Definition in file itsolver_util.inl.

9.54 linklist.inl File Reference

Utilies for link list data structure.

Macros

- #define LIST_HEAD -1
- #define LIST_TAIL -2

9.54.1 Detailed Description

Utilies for link list data structure.

Note

These linked-list operations are adapted from hypre 2.0

Definition in file linklist.inl.

9.54.2 Macro Definition Documentation

9.54.2.1 #define LIST_HEAD -1

head of the linked list

Definition at line 7 of file linklist.inl.

9.54.2.2 #define LIST_TAIL -2

tail of the linked list

Definition at line 8 of file linklist.inl.

9.55 lu.c File Reference 223

9.55 lu.c File Reference

LU decomposition and direct solve for dense matrix.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

• SHORT fasp_smat_lu_decomp (REAL *A, INT pivot[], INT n)

LU decomposition of A usind Doolittle's method.

SHORT fasp_smat_lu_solve (REAL *A, REAL b[], INT pivot[], REAL x[], INT n)

Solving Ax=b using LU decomposition.

9.55.1 Detailed Description

LU decomposition and direct solve for dense matrix.

Definition in file lu.c.

9.55.2 Function Documentation

```
9.55.2.1 SHORT fasp_smat_lu_decomp ( REAL * A, INT pivot[], INT n )
```

LU decomposition of A usind Doolittle's method.

Parameters

Α	Pointer to the full matrix
pivot	Pivoting positions
n	Size of matrix A

Returns

SUCCESS if succeed, RUN FAIL if fail

Note

Use Doolittle's method to decompose the n x n matrix A into a unit lower triangular matrix L and an upper triangular matrix U such that A = LU. The matrices L and U replace the matrix A. The diagonal elements of L are 1 and are not stored.

The Doolittle method with partial pivoting is: Determine the pivot row and interchange the current row with the pivot row, then assuming that row k is the current row, k = 0, ..., n - 1 evaluate in order the following pair of expressions U[k][j] = A[k][j] - (L[k][0]*U[0][j] + ... + L[k][k-1]*U[k-1][j]) for j = k, k+1, ..., n-1 L[i][k] = (A[i][k] - (L[i][0]*U[0][k] + ... + L[i][k-1]*U[k-1][k])) / U[k][k] for i = k+1, ..., n-1.

Author

Xuehai Huang

Date

04/02/2009

Definition at line 46 of file lu.c.

9.55.2.2 SHORT fasp_smat_lu_solve (REAL * A, REAL b[], INT pivot[], REAL x[], INT n)

Solving Ax=b using LU decomposition.

Parameters

Α	Pointer to the full matrix
b	Right hand side array
pivot	Pivoting positions
X	Pointer to the solution array
n	Size of matrix A

Returns

SUCCESS if succeed, RUN_FAIL if failed

Note

This routine uses Doolittle's method to solve the linear equation Ax = b. This routine is called after the matrix A has been decomposed into a product of a unit lower triangular matrix L and an upper triangular matrix U with pivoting. The solution proceeds by solving the linear equation Ly = b for y and subsequently solving the linear equation Ux = y for x.

Author

Xuehai Huang

Date

04/02/2009

Definition at line 117 of file lu.c.

9.56 memory.c File Reference

Memory allocation and deallocation.

```
#include "fasp.h"
```

Functions

- void * fasp_mem_calloc (LONGLONG size, INT type)
- void * fasp_mem_realloc (void *oldmem, LONG tsize)

Reallocate, initiate, and check memory.

void fasp_mem_free (void *mem)

Free up previous allocated memory body.

void fasp_mem_usage ()

Show total allocated memory currently.

SHORT fasp_mem_check (void *ptr, char *message, INT ERR)

Check wether a point is null or not.

• SHORT fasp_mem_iludata_check (ILU_data *iludata)

Check wether a ILU_data has enough work space.

SHORT fasp_mem_dcsr_check (dCSRmat *A)

Check wether a dCSRmat A has sucessfully allocated memory.

Variables

- unsigned INT total_alloc_mem = 0
- unsigned INT total_alloc_count = 0

9.56.1 Detailed Description

Memory allocation and deallocation.

Definition in file memory.c.

9.56.2 Function Documentation

9.56.2.1 SHORT fasp_mem_check (void * ptr, char * message, INT ERR)

Check wether a point is null or not.

Parameters

ptr	Void pointer to be checked
message	Error message to print
ERR	Integer error code

Returns

SUCCESS or error code

Author

Chensong Zhang

Date

11/16/2009

Definition at line 191 of file memory.c.

9.56.2.2 SHORT fasp_mem_dcsr_check (dCSRmat * A)

Check wether a dCSRmat A has sucessfully allocated memory.

Parameters

A Pointer to be cheked

Returns

SUCCESS if success, else ERROR message (negative value)

Author

Xiaozhe Hu

Date

11/27/09

Definition at line 241 of file memory.c.

9.56.2.3 void fasp_mem_free (void * mem)

Free up previous allocated memory body.

Parameters

mem Pointer to the memory body need to be freed

Returns

NULL pointer

Author

Chensong Zhang

Date

2010/12/24

Definition at line 144 of file memory.c.

9.56.2.4 SHORT fasp_mem_iludata_check (ILU_data * iludata)

Check wether a ILU_data has enough work space.

Parameters

iludata Pointer to be cheked

Returns

SUCCESS if success, else ERROR (negative value)

Author

Xiaozhe Hu, Chensong Zhang

Date

11/27/09

Definition at line 215 of file memory.c.

9.56.2.5 void * fasp_mem_realloc (void * oldmem, LONG type)

Reallocate, initiate, and check memory.

Parameters

oldmem	Pointer to the existing mem block
type	Size of memory blocks

Returns

Void pointer to the reallocated memory

Author

Chensong Zhang

Date

2010/08/12

Modified by Chunsheng Feng on 07/23/2013 Modified by Chensong Zhang on 07/30/2013: return warning if failed Definition at line 110 of file memory.c.

9.56.2.6 void fasp_mem_usage ()

Show total allocated memory currently.

Author

Chensong Zhang

Date

2010/08/12

Definition at line 169 of file memory.c.

9.56.3 Variable Documentation

9.56.3.1 unsigned INT total_alloc_count = 0

total allocation times

Definition at line 33 of file memory.c.

```
9.56.3.2 unsigned INT total_alloc_mem = 0
```

total allocated memory

Definition at line 32 of file memory.c.

9.57 message.c File Reference

Output some useful messages.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void print_itinfo (const INT ptrlvl, const INT stop_type, const INT iter, const REAL relres, const REAL absres, const REAL factor)

Print out iteration information for iterative solvers.

void print_amgcomplexity (AMG_data *mgl, const SHORT prtlvl)

Print complexities of AMG method.

• void print_amgcomplexity_bsr (AMG_data_bsr *mgl, const SHORT prtlvl)

Print complexities of AMG method for BSR matrices.

void print_cputime (const char *message, const REAL cputime)

Print CPU walltime.

• void print_message (const INT ptrlvl, const char *message)

Print output information if necessary.

void fasp_chkerr (const SHORT status, const char *fctname)

Check error status and print out error messages before quit.

9.57.1 Detailed Description

Output some useful messages.

Note

These routines are meant for internal use only.

Definition in file message.c.

9.57.2 Function Documentation

9.57.2.1 void fasp_chkerr (const SHORT status, const char * fctname)

Check error status and print out error messages before quit.

Parameters

status	Error status
fctname	Function name where this routine is called

Author

Chensong Zhang

Date

01/10/2012

Definition at line 185 of file message.c.

9.57.2.2 void void print_amgcomplexity (AMG_data * mgl, const SHORT prtlvl)

Print complexities of AMG method.

Parameters

mgl	Multilevel hierachy for AMG
prtlvl	How much information to print

Author

Chensong Zhang

Date

11/16/2009

Definition at line 79 of file message.c.

9.57.2.3 void void print_amgcomplexity_bsr (AMG_data_bsr * mgl, const SHORT prtlvl)

Print complexities of AMG method for BSR matrices.

Parameters

mgl	Multilevel hierachy for AMG
prtlvl	How much information to print

Author

Chensong Zhang

Date

05/10/2013

Definition at line 115 of file message.c.

9.57.2.4 void void print_cputime (const char * message, const REAL cputime)

Print CPU walltime.

Parameters

message	Some string to print out
cputime	Walltime since start to end

Author

Chensong Zhang

Date

04/10/2012

Definition at line 151 of file message.c.

9.57.2.5 void print_itinfo (const INT ptrlvl, const INT stop_type, const INT iter, const REAL relres, const REAL absres, const REAL factor)

Print out iteration information for iterative solvers.

Parameters

ptrlvl	Level for output
stop_type	Type of stopping criteria
iter	Number of iterations
relres	Relative residual of different kinds
absres	Absolute residual of different kinds
factor	Contraction factor

Author

Chensong Zhang

Date

11/16/2009

Modified by Chensong Zhang on 03/28/2013: Output initial guess Modified by Chensong Zhang on 04/05/2013: Fix a typo

Definition at line 36 of file message.c.

9.57.2.6 void print_message (const INT ptrlvl, const char * message)

Print output information if necessary.

Parameters

ptrlvl	Level for output
message	Error message to print

Author

Chensong Zhang

Date

11/16/2009

Definition at line 168 of file message.c.

9.58 messages.h File Reference

Definition of all kinds of messages, including error messages, solver types, etc.

Macros

```
• #define TRUE 1
```

Definition of logic type.

- #define FALSE 0
- #define ON 1

Definition of switch.

- #define OFF 0
- #define PRINT NONE 0

Print level for all subroutines - not including DEBUG output.

- #define PRINT MIN 1
- #define PRINT SOME 2
- #define PRINT MORE 4
- #define PRINT_MOST 8
- #define PRINT_ALL 10
- #define MAT_FREE 0

Definition of matrix format.

- #define MAT CSR 1
- #define MAT BSR 2
- #define MAT_STR 3
- #define MAT bCSR 4
- #define MAT_bBSR 5
- #define MAT_CSRL 6
- #define MAT_SymCSR 7
- #define ERROR_OPEN_FILE -10

Definition of return status and error messages.

- #define ERROR_WRONG_FILE -11
- #define ERROR_INPUT_PAR -13
- #define ERROR_REGRESS -14
- #define ERROR_NUM_BLOCKS -18
- #define ERROR_MISC -19
- #define ERROR ALLOC MEM -20
- #define ERROR DATA STRUCTURE -21
- #define ERROR_DATA_ZERODIAG -22
- #define ERROR DUMMY VAR -23
- #define ERROR_AMG_INTERP_TYPE -30
- #define ERROR_AMG_SMOOTH_TYPE -31
- #define ERROR AMG COARSE TYPE -32
- #define ERROR_AMG_COARSEING -33

- #define ERROR_SOLVER_TYPE -40
- #define ERROR SOLVER PRECTYPE -41
- #define ERROR_SOLVER_STAG -42
- #define ERROR_SOLVER_SOLSTAG -43
- #define ERROR SOLVER TOLSMALL -44
- #define ERROR SOLVER ILUSETUP -45
- #define ERROR SOLVER MISC -46
- #define ERROR_SOLVER_MAXIT -48
- #define ERROR_SOLVER_EXIT -49
- #define ERROR_QUAD_TYPE -60
- #define ERROR QUAD DIM -61
- #define RUN FAIL -99
- #define SUCCESS 0
- #define SOLVER CG 1

Definition of solver types for iterative methods.

- #define SOLVER BiCGstab 2
- #define SOLVER MinRes 3
- #define SOLVER GMRES 4
- #define SOLVER VGMRES 5
- #define SOLVER VFGMRES 6
- #define SOLVER GCG 7
- #define SOLVER SCG 11
- #define SOLVER_SBiCGstab 12
- #define SOLVER SMinRes 13
- #define SOLVER SGMRES 14
- #define SOLVER_SVGMRES 15
- #define SOLVER SVFGMRES 16
- #define SOLVER SGCG 17
- #define SOLVER AMG 21
- #define SOLVER FMG 22
- #define SOLVER_SUPERLU 31

Definition of solver types for direct methods (requires external libs)

- #define SOLVER UMFPACK 32
- #define SOLVER_MUMPS 33
- #define STOP_REL_RES 1

Definition of iterative solver stopping criteria types.

- #define STOP REL PRECRES 2
- #define STOP_MOD_REL_RES 3
- #define PREC NULL 0

Definition of preconditioner type for iterative methods.

- #define PREC DIAG 1
- #define PREC AMG 2
- #define PREC FMG 3
- #define PREC_ILU 4
- #define PREC SCHWARZ 5
- #define CLASSIC_AMG 1

Definition of AMG types.

- #define SA AMG 2
- #define UA AMG 3
- #define V CYCLE 1

Definition of cycle types.

- #define W_CYCLE 2
- #define AMLI CYCLE 3
- #define NL_AMLI_CYCLE 4
- #define SMOOTHER_JACOBI 1

Definition of standard smoother types.

- #define SMOOTHER GS 2
- #define SMOOTHER SGS 3
- #define SMOOTHER_CG 4
- #define SMOOTHER SOR 5
- #define SMOOTHER_SSOR 6
- #define SMOOTHER_GSOR 7
- #define SMOOTHER_SGSOR 8
- #define SMOOTHER_POLY 9
- #define SMOOTHER L1DIAG 10
- #define SMOOTHER_BLKOIL 11

Definition of specialized smoother types.

• #define COARSE_RS 1

Definition of coarsening types.

- #define COARSE_CR 3
- #define COARSE_AC 4
- #define INTERP_DIR 1

Definition of interpolation types.

- #define INTERP_STD 2
- #define INTERP_ENG 3
- #define UNPT -1

Type of vertices (dofs) for C/F splitting.

- #define FGPT 0
- #define CGPT 1
- #define ISPT 2
- #define NO_ORDER 0

Definition of smoothing order.

- #define CF_ORDER 1
- #define USERDEFINED 0

Type of ordering for smoothers.

- #define CPFIRST 1
- #define FPFIRST -1
- #define ASCEND 12
- #define DESCEND 21
- #define ILUk 1

Type of ILU methods.

- #define ILUt 2
- #define ILUtp 3

9.58.1 Detailed Description

Definition of all kinds of messages, including error messages, solver types, etc.

Note

This is internal use only.

Created by Chensong Zhang on 03/20/2010. Modified by Chensong Zhang on 12/06/2011. Modified by Chensong Zhang on 12/25/2011. Modified by Chensong Zhang on 04/22/2012. Modified by Ludmil Zikatanov on 02/15/2013: CG -> SMOOTHER_CG. Modified by Chensong Zhang on 02/16/2013: GS -> SMOOTHER_GS, etc. Modified by Chensong Zhang on 04/09/2013: Add safe krylov methods.

Modified by Chensong Zhang on 09/22/2013: Clean up Doxygen.

Definition in file messages.h.

9.58.2 Macro Definition Documentation

9.58.2.1 #define AMLI_CYCLE 3

AMLI-cycle

Definition at line 151 of file messages.h.

9.58.2.2 #define ASCEND 12

Asscending order

Definition at line 207 of file messages.h.

9.58.2.3 #define CF_ORDER 1

C/F order smoothing

Definition at line 199 of file messages.h.

9.58.2.4 #define CGPT 1

coarse grid points

Definition at line 192 of file messages.h.

9.58.2.5 #define CLASSIC_AMG 1

Definition of AMG types.

classic AMG

Definition at line 142 of file messages.h.

9.58.2.6 #define COARSE_AC 4

Aggressive coarsening

Definition at line 178 of file messages.h.

9.58.2.7 #define COARSE_CR 3

Compatible relaxation

Definition at line 177 of file messages.h.

9.58.2.8 #define COARSE_RS 1

Definition of coarsening types.

Classical coarsening

Definition at line 176 of file messages.h.

9.58.2.9 #define CPFIRST 1

C-points first order

Definition at line 205 of file messages.h.

9.58.2.10 #define DESCEND 21

Dsscending order

Definition at line 208 of file messages.h.

9.58.2.11 #define ERROR_ALLOC_MEM -20

fail to allocate memory

Definition at line 67 of file messages.h.

9.58.2.12 #define ERROR_AMG_COARSE_TYPE -32

unknown coarsening type

Definition at line 74 of file messages.h.

9.58.2.13 #define ERROR_AMG_COARSEING -33

coarsening step failed to complete

Definition at line 75 of file messages.h.

9.58.2.14 #define ERROR_AMG_INTERP_TYPE -30

unknown interpolation type

Definition at line 72 of file messages.h.

9.58.2.15 #define ERROR_AMG_SMOOTH_TYPE -31

unknown smoother type

Definition at line 73 of file messages.h.

9.58.2.16 #define ERROR_DATA_STRUCTURE -21

matrix or vector structures

Definition at line 68 of file messages.h.

9.58.2.17 #define ERROR_DATA_ZERODIAG -22

matrix has zero diagonal entries

Definition at line 69 of file messages.h.

9.58.2.18 #define ERROR_DUMMY_VAR -23

unexpected input data

Definition at line 70 of file messages.h.

9.58.2.19 #define ERROR_INPUT_PAR -13

wrong input argument

Definition at line 62 of file messages.h.

9.58.2.20 #define ERROR_MISC -19

other error

Definition at line 65 of file messages.h.

9.58.2.21 #define ERROR_NUM_BLOCKS -18

wrong number of blocks

Definition at line 64 of file messages.h.

9.58.2.22 #define ERROR_OPEN_FILE -10

Definition of return status and error messages.

fail to open a file

Definition at line 60 of file messages.h.

9.58.2.23 #define ERROR_QUAD_DIM -61

unsupported quadrature dim

Definition at line 88 of file messages.h.

9.58.2.24 #define ERROR_QUAD_TYPE -60

unknown quadrature type

Definition at line 87 of file messages.h.

9.58.2.25 #define ERROR_REGRESS -14

regression test fail

Definition at line 63 of file messages.h.

9.58.2.26 #define ERROR_SOLVER_EXIT -49

solver does not quit successfully

Definition at line 85 of file messages.h.

9.58.2.27 #define ERROR_SOLVER_ILUSETUP -45

ILU setup error

Definition at line 82 of file messages.h.

9.58.2.28 #define ERROR_SOLVER_MAXIT -48

maximal iteration number exceeded

Definition at line 84 of file messages.h.

9.58.2.29 #define ERROR_SOLVER_MISC -46

misc solver error during run time

Definition at line 83 of file messages.h.

9.58.2.30 #define ERROR_SOLVER_PRECTYPE -41

unknow precond type

Definition at line 78 of file messages.h.

9.58.2.31 #define ERROR_SOLVER_SOLSTAG -43

solver's solution is too small

Definition at line 80 of file messages.h.

9.58.2.32 #define ERROR_SOLVER_STAG -42

solver stagnates

Definition at line 79 of file messages.h.

9.58.2.33 #define ERROR_SOLVER_TOLSMALL -44

solver's tolerance is too small

Definition at line 81 of file messages.h.

9.58.2.34 #define ERROR_SOLVER_TYPE -40

unknown solver type

Definition at line 77 of file messages.h.

9.58.2.35 #define ERROR_WRONG_FILE -11

input contains wrong format

Definition at line 61 of file messages.h.

9.58.2.36 #define FALSE 0

logic FALSE

Definition at line 27 of file messages.h.

9.58.2.37 #define FGPT 0

fine grid points

Definition at line 191 of file messages.h.

9.58.2.38 #define FPFIRST -1

F-points first order

Definition at line 206 of file messages.h.

9.58.2.39 #define ILUk 1

Type of ILU methods.

ILUk

Definition at line 213 of file messages.h.

9.58.2.40 #define ILUt 2

ILUt

Definition at line 214 of file messages.h.

9.58.2.41 #define ILUtp 3

ILUtp

Definition at line 215 of file messages.h.

9.58.2.42 #define INTERP_DIR 1

Definition of interpolation types.

Direct interpolation

Definition at line 183 of file messages.h.

9.58.2.43 #define INTERP_ENG 3

energy minimization interp in C

Definition at line 185 of file messages.h.

9.58.2.44 #define INTERP_STD 2

Standard interpolation

Definition at line 184 of file messages.h.

9.58.2.45 #define ISPT 2

isolated points

Definition at line 193 of file messages.h.

9.58.2.46 #define MAT_bBSR 5

block matrix of BSR for borded systems

Definition at line 53 of file messages.h.

9.58.2.47 #define MAT_bCSR 4

block matrix of CSR

Definition at line 52 of file messages.h.

9.58.2.48 #define MAT_BSR 2

blockwise compressed sparse row

Definition at line 50 of file messages.h.

9.58.2.49 #define MAT_CSR 1

compressed sparse row

Definition at line 49 of file messages.h.

9.58.2.50 #define MAT_CSRL 6

modified CSR to reduce cache missing

Definition at line 54 of file messages.h.

9.58.2.51 #define MAT_FREE 0

Definition of matrix format.

matrix-free format: only mxv action

Definition at line 48 of file messages.h.

9.58.2.52 #define MAT_STR 3

structured sparse matrix

Definition at line 51 of file messages.h.

9.58.2.53 #define MAT_SymCSR 7

symmetric CSR format

Definition at line 55 of file messages.h.

9.58.2.54 #define NL_AMLI_CYCLE 4

Nonlinear AMLI-cycle

Definition at line 152 of file messages.h.

9.58.2.55 #define NO_ORDER 0

Definition of smoothing order.

Natural order smoothing

Definition at line 198 of file messages.h.

9.58.2.56 #define OFF 0

turn off certain parameter

Definition at line 33 of file messages.h.

9.58.2.57 #define ON 1

Definition of switch.

turn on certain parameter

Definition at line 32 of file messages.h.

9.58.2.58 #define PREC_AMG 2

with AMG precond

Definition at line 134 of file messages.h.

9.58.2.59 #define PREC_DIAG 1

with diagonal precond

Definition at line 133 of file messages.h.

9.58.2.60 #define PREC_FMG 3

with full AMG precond

Definition at line 135 of file messages.h.

9.58.2.61 #define PREC_ILU 4

with ILU precond

Definition at line 136 of file messages.h.

9.58.2.62 #define PREC_NULL 0

Definition of preconditioner type for iterative methods.

with no precond

Definition at line 132 of file messages.h.

9.58.2.63 #define PREC_SCHWARZ 5

with Schwarz preconditioner

Definition at line 137 of file messages.h.

9.58.2.64 #define PRINT_ALL 10

everything: all printouts allowed

Definition at line 43 of file messages.h.

9.58.2.65 #define PRINT_MIN 1

quiet: minimal print, like convergence Definition at line 39 of file messages.h.

9.58.2.66 #define PRINT_MORE 4

more: print more useful information

Definition at line 41 of file messages.h.

9.58.2.67 #define PRINT_MOST 8

most: maximal printouts, no disk files Definition at line 42 of file messages.h.

9.58.2.68 #define PRINT_NONE 0

Print level for all subroutines – not including DEBUG output.

slient: no printout at all

Definition at line 38 of file messages.h.

9.58.2.69 #define PRINT_SOME 2

some: print cpu time, iteration number Definition at line 40 of file messages.h.

9.58.2.70 #define RUN_FAIL -99

general failure

Definition at line 90 of file messages.h.

9.58.2.71 #define SA_AMG 2

smoothed aggregation AMG

Definition at line 143 of file messages.h.

9.58.2.72 #define SMOOTHER_BLKOIL 11

Definition of specialized smoother types.

Used in monolithic AMG for black-oil

Definition at line 171 of file messages.h.

9.58.2.73 #define SMOOTHER_CG 4

CG as a smoother

Definition at line 160 of file messages.h.

9.58.2.74 #define SMOOTHER_GS 2

Gauss-Seidel smoother

Definition at line 158 of file messages.h.

9.58.2.75 #define SMOOTHER_GSOR 7

GS + SOR smoother

Definition at line 163 of file messages.h.

9.58.2.76 #define SMOOTHER_JACOBI 1

Definition of standard smoother types.

Jacobi smoother

Definition at line 157 of file messages.h.

9.58.2.77 #define SMOOTHER_L1DIAG 10

L1 norm diagonal scaling smoother

Definition at line 166 of file messages.h.

9.58.2.78 #define SMOOTHER_POLY 9

Polynomial smoother

Definition at line 165 of file messages.h.

9.58.2.79 #define SMOOTHER_SGS 3

symm Gauss-Seidel smoother

Definition at line 159 of file messages.h.

9.58.2.80 #define SMOOTHER_SGSOR 8

SGS + SSOR smoother

Definition at line 164 of file messages.h.

9.58.2.81 #define SMOOTHER_SOR 5

SOR smoother

Definition at line 161 of file messages.h.

9.58.2.82 #define SMOOTHER_SSOR 6

SSOR smoother

Definition at line 162 of file messages.h.

9.58.2.83 #define SOLVER_AMG 21

AMG as an iterative solver

Definition at line 112 of file messages.h.

9.58.2.84 #define SOLVER_BiCGstab 2

Biconjugate Gradient Stabilized

Definition at line 97 of file messages.h.

9.58.2.85 #define SOLVER_CG 1

Definition of solver types for iterative methods.

Conjugate Gradient

Definition at line 96 of file messages.h.

9.58.2.86 #define SOLVER_FMG 22

Full AMG as an solver

Definition at line 113 of file messages.h.

9.58.2.87 #define SOLVER_GCG 7

Generalized Conjugate Gradient

Definition at line 102 of file messages.h.

9.58.2.88 #define SOLVER_GMRES 4

Generalized Minimal Residual

Definition at line 99 of file messages.h.

9.58.2.89 #define SOLVER_MinRes 3

Minimal Residual

Definition at line 98 of file messages.h.

9.58.2.90 #define SOLVER_MUMPS 33

MUMPS Direct Solver

Definition at line 120 of file messages.h.

9.58.2.91 #define SOLVER_SBiCGstab 12

BiCGstab with safe net

Definition at line 105 of file messages.h.

9.58.2.92 #define SOLVER_SCG 11

Conjugate Gradient with safe net

Definition at line 104 of file messages.h.

9.58.2.93 #define SOLVER_SGCG 17

GCG with safe net

Definition at line 110 of file messages.h.

9.58.2.94 #define SOLVER_SGMRES 14

GMRes with safe net

Definition at line 107 of file messages.h.

9.58.2.95 #define SOLVER_SMinRes 13

MinRes with safe net

Definition at line 106 of file messages.h.

9.58.2.96 #define SOLVER_SUPERLU 31

Definition of solver types for direct methods (requires external libs)

SuperLU Direct Solver

Definition at line 118 of file messages.h.

9.58.2.97 #define SOLVER_SVFGMRES 16

Variable-restart FGMRES with safe net

Definition at line 109 of file messages.h.

9.58.2.98 #define SOLVER_SVGMRES 15

Variable-restart GMRES with safe net

Definition at line 108 of file messages.h.

9.58.2.99 #define SOLVER_UMFPACK 32

UMFPack Direct Solver

Definition at line 119 of file messages.h.

9.58.2.100 #define SOLVER_VFGMRES 6

Variable Restarting Flexible GMRES

Definition at line 101 of file messages.h.

9.58.2.101 #define SOLVER_VGMRES 5

Variable Restarting GMRES

Definition at line 100 of file messages.h.

9.58.2.102 #define STOP_MOD_REL_RES 3

modified relative residual ||r||/||x||

Definition at line 127 of file messages.h.

9.58.2.103 #define STOP_REL_PRECRES 2

relative B-residual $||r||_B/||b||_B$

Definition at line 126 of file messages.h.

9.58.2.104 #define STOP_REL_RES 1

Definition of iterative solver stopping criteria types.

relative residual ||r||/||b||

Definition at line 125 of file messages.h.

9.58.2.105 #define SUCCESS 0

return from funtion successfully

Definition at line 91 of file messages.h.

9.58.2.106 #define TRUE 1

Definition of logic type.

logic TRUE

Definition at line 26 of file messages.h.

9.58.2.107 #define UA_AMG 3

unsmoothed aggregation AMG

Definition at line 144 of file messages.h.

9.58.2.108 #define UNPT -1

Type of vertices (dofs) for C/F splitting.

undetermined points

Definition at line 190 of file messages.h.

9.58.2.109 #define USERDEFINED 0

Type of ordering for smoothers.

USERDEFINED order

Definition at line 204 of file messages.h.

9.58.2.110 #define V_CYCLE 1

Definition of cycle types.

V-cycle

Definition at line 149 of file messages.h.

9.58.2.111 #define W_CYCLE 2

W-cycle

Definition at line 150 of file messages.h.

9.59 mg_util.inl File Reference

Routines for algebraic multigrid cycles.

9.59.1 Detailed Description

Routines for algebraic multigrid cycles.

Definition in file mg_util.inl.

9.60 mgcycle.c File Reference

Abstract non-recursive multigrid cycle.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "forts_ns.h"
#include "mg_util.inl"
```

Functions

• void fasp_solver_mgcycle (AMG_data *mgl, AMG_param *param)

Solve Ax=b with non-recursive multigrid cycle.

void fasp_solver_mgcycle_bsr (AMG_data_bsr *mgl, AMG_param *param)

Solve Ax=b with non-recursive multigrid cycle.

9.60.1 Detailed Description

Abstract non-recursive multigrid cycle.

Definition in file mgcycle.c.

9.60.2 Function Documentation

```
9.60.2.1 void fasp_solver_mgcycle ( AMG_data * mgl, AMG_param * param )
```

Solve Ax=b with non-recursive multigrid cycle.

Parameters

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param

Author

Chensong Zhang

Date

10/06/2010

Modified by Chensong Zhang on 12/13/2011 Modified by Chensong Zhang on 02/27/2013: update direct solvers. Definition at line 41 of file mgcycle.c.

```
9.60.2.2 void fasp_solver_mgcycle_bsr ( AMG_data_bsr * mgl, AMG_param * param )
```

Solve Ax=b with non-recursive multigrid cycle.

Parameters

mgl	Pointer to AMG data: AMG_data_bsr
param	Pointer to AMG parameters: AMG_param

Author

Xiaozhe Hu

Date

08/07/2011

Definition at line 294 of file mgcycle.c.

9.61 mgrecur.c File Reference

Abstract multigrid cycle – recursive version.

```
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "mg_util.inl"
```

Functions

• void fasp_solver_mgrecur (AMG_data *mgl, AMG_param *param, INT level)

Solve Ax=b with recursive multigrid K-cycle.

9.61.1 Detailed Description

Abstract multigrid cycle - recursive version.

Definition in file mgrecur.c.

9.61.2 Function Documentation

```
9.61.2.1 void fasp_solver_mgrecur ( AMG_data * mgl, AMG_param * param, INT level )
```

Solve Ax=b with recursive multigrid K-cycle.

Parameters

mgl	Pointer to AMG data: AMG_data
param	Pointer to AMG parameters: AMG_param
level	Index of the current level

Author

Xuehai Huang, Chensong Zhang

Date

04/06/2010

Modified by Chensong Zhang on 01/10/2012 Modified by Chensong Zhang on 02/27/2013: update direct solvers. Definition at line 31 of file mgrecur.c.

9.62 ordering.c File Reference

A collection of ordering, merging, removing duplicated integers functions.

```
#include "fasp.h"
```

Functions

- INT fasp_BinarySearch (INT *list, INT value, INT list_length)
 - Binary Search.
- INT fasp_aux_unique (INT numbers[], INT size)

Remove duplicates in an sorted (ascending order) array.

void fasp_aux_merge (INT numbers[], INT work[], INT left, INT mid, INT right)

Merge two sorted arraies.

void fasp_aux_msort (INT numbers[], INT work[], INT left, INT right)

Sort the INT array ascendingly with the merge sort algorithm.

void fasp_aux_iQuickSort (INT *a, INT left, INT right)

Sort the array (INT type) ascendingly with the quick sorting algorithm.

void fasp_aux_dQuickSort (REAL *a, INT left, INT right)

Sort the array (REAL type) ascendingly with the quick sorting algorithm.

void fasp_aux_iQuickSortIndex (INT *a, INT left, INT right, INT *index)

Reorder the index of (INT type) so that 'a' is in ascending order.

void fasp aux dQuickSortIndex (REAL *a, INT left, INT right, INT *index)

Reorder the index of (REAL type) so that 'a' is ascending in such order.

9.62.1 Detailed Description

A collection of ordering, merging, removing duplicated integers functions.

Definition in file ordering.c.

9.62.2 Function Documentation

9.62.2.1 void fasp_aux_dQuickSort (REAL * a, INT left, INT right)

Sort the array (REAL type) ascendingly with the quick sorting algorithm.

Parameters

а	Pointer to the array needed to be sorted
left	Starting index
right	Ending index

Author

Zhiyang Zhou

Date

2009/11/28

Note

'left' and 'right' are usually set to be 0 and n-1, respectively where n is the length of 'a'.

Definition at line 238 of file ordering.c.

9.62.2.2 void fasp_aux_dQuickSortIndex (REAL * a, INT left, INT right, INT * index)

Reorder the index of (REAL type) so that 'a' is ascending in such order.

Parameters

а	Pointer to the array
left	Starting index
right	Ending index
index	Index of 'a' (out)

Author

Zhiyang Zhou

Date

2009/12/02

Note

'left' and 'right' are usually set to be 0 and n-1,respectively,where n is the length of 'a'. 'index' should be initialized in the nature order and it has the same length as 'a'.

Definition at line 319 of file ordering.c.

9.62.2.3 void fasp_aux_iQuickSort (INT * a, INT left, INT right)

Sort the array (INT type) ascendingly with the quick sorting algorithm.

а	Pointer to the array needed to be sorted
left	Starting index
right	Ending index

Author

Zhiyang Zhou

Date

11/28/2009

Note

'left' and 'right' are usually set to be 0 and n-1, respectively where n is the length of 'a'.

Definition at line 200 of file ordering.c.

9.62.2.4 void fasp_aux_iQuickSortIndex (INT * a, INT left, INT right, INT * index)

Reorder the index of (INT type) so that 'a' is in ascending order.

Parameters

а	Pointer to the array
left	Starting index
right	Ending index
index	Index of 'a' (out)

Author

Zhiyang Zhou

Date

2009/12/02

Note

'left' and 'right' are usually set to be 0 and n-1,respectively,where n is the length of 'a'. 'index' should be initialized in the nature order and it has the same length as 'a'.

Definition at line 278 of file ordering.c.

9.62.2.5 void fasp_aux_merge (INT numbers[], INT work[], INT left, INT mid, INT right)

Merge two sorted arraies.

Parameters

numbers	Pointer to the array needed to be sorted
work	Pointer to the work array with same size as numbers
left	Starting index of array 1
mid	Starting index of array 2
right	Ending index of array 1 and 2

Author

Chensong Zhang

Date

11/21/2010

Note

Both arraies are stored in numbers! Arraies should be pre-sorted!

Definition at line 107 of file ordering.c.

9.62.2.6 void fasp_aux_msort (INT numbers[], INT work[], INT left, INT right)

Sort the INT array ascendingly with the merge sort algorithm.

Parameters

numbers	Pointer to the array needed to be sorted
work	Pointer to the work array with same size as numbers
left	Starting index
right	Ending index

Author

Chensong Zhang

Date

11/21/2010

Note

'left' and 'right' are usually set to be 0 and n-1, respectively

Definition at line 169 of file ordering.c.

9.62.2.7 INT fasp_aux_unique (INT numbers[], INT size)

Remove duplicates in an sorted (ascending order) array.

numbers	Pointer to the array needed to be sorted (in/out)
size	Length of the target array

Returns

New size after removing duplicates

Author

Chensong Zhang

Date

11/21/2010

Note

Operation is in place. Does not use any extra or temprary storage.

Definition at line 74 of file ordering.c.

9.62.2.8 INT fasp_BinarySearch (INT * list, INT value, INT list_length)

Binary Search.

Parameters

list	Pointer to a set of values
value	The target
list_length	Length of the array list

Returns

The location of value in array list if successed, otherwise, return -1.

Author

Chunsheng Feng

Date

03/01/2011

Definition at line 29 of file ordering.c.

9.63 parameters.c File Reference

Initialize, set, or print input data and parameters.

```
#include <stdio.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void fasp_param_init (char *inputfile, input_param *inparam, itsolver_param *itsparam, AMG_param *amgparam, ILU_param *iluparam, Schwarz_param *schparam)

Initialize parameters, global variables, etc.

void fasp_param_input_init (input_param *inparam)

Initialize input parameters.

void fasp_param_amg_init (AMG_param *amgparam)

Initialize AMG parameters.

void fasp_param_solver_init (itsolver_param *itsparam)

Initialize itsolver param.

void fasp param ilu init (ILU param *iluparam)

Initialize ILU parameters.

void fasp param schwarz init (Schwarz param *schparam)

Initialize Schwarz parameters.

void fasp_param_amg_set (AMG_param *param, input_param *inparam)

Set AMG param from INPUT.

void fasp_param_ilu_set (ILU_param *iluparam, input_param *inparam)

Set ILU param with INPUT.

void fasp_param_schwarz_set (Schwarz_param *schparam, input_param *inparam)

Set Schwarz_param with INPUT.

void fasp_param_solver_set (itsolver_param *itsparam, input_param *inparam)

Set itsolver_param with INPUT.

void fasp_precond_data_null (precond_data *pcdata)

Initialize precond_data.

void fasp_param_amg_to_prec (precond_data *pcdata, AMG_param *amgparam)

Set precond_data with AMG_param.

void fasp_param_prec_to_amg (AMG_param *amgparam, precond_data *pcdata)

Set AMG_param with precond_data.

void fasp_param_amg_to_prec_bsr (precond_data_bsr *pcdata, AMG_param *amgparam)

Set precond_data_bsr with AMG_param.

void fasp_param_prec_to_amg_bsr (AMG_param *amgparam, precond_data_bsr *pcdata)

Set AMG_param with precond_data.

void fasp_param_amg_print (AMG_param *param)

Print out AMG parameters.

• void fasp_param_ilu_print (ILU_param *param)

Print out ILU parameters.

void fasp_param_schwarz_print (Schwarz_param *param)

Print out Schwarz parameters.

void fasp param solver print (itsolver param *param)

Print out itsolver parameters.

9.63.1 Detailed Description

Initialize, set, or print input data and parameters.

Definition in file parameters.c.

9.63.2 Function Documentation

9.63.2.1 void fasp_param_amg_init (AMG_param * amgparam)

Initialize AMG parameters.

Parameters

amgparam

Author

Chensong Zhang

Date

2010/04/03

Definition at line 153 of file parameters.c.

9.63.2.2 void fasp_param_amg_print (AMG_param * param)

Print out AMG parameters.

Parameters

param	Parameters for AMG
-------	--------------------

Author

Chensong Zhang

Date

2010/03/22

Definition at line 573 of file parameters.c.

9.63.2.3 void fasp_param_amg_set (AMG_param * param, input_param * inparam)

Set AMG_param from INPUT.

Parameters

param	Parameters for AMG
inparam	Input parameters

Author

Chensong Zhang

Date

2010/03/23

Definition at line 275 of file parameters.c.

9.63.2.4 void fasp_param_amg_to_prec (precond_data * pcdata, AMG_param * amgparam)

Set precond_data with AMG_param.

pcdata	Preconditioning data structure
amgparam	Parameters for AMG

Author

Chensong Zhang

Date

2011/01/10

Definition at line 446 of file parameters.c.

9.63.2.5 void fasp_param_amg_to_prec_bsr (precond_data_bsr * pcdata, AMG_param * amgparam)

Set precond_data_bsr with AMG_param.

Parameters

pcdata	Preconditioning data structure
amgparam	Parameters for AMG

Author

Xiaozhe Hu

Date

02/06/2012

Definition at line 511 of file parameters.c.

9.63.2.6 void fasp_param_ilu_init (ILU_param * iluparam)

Initialize ILU parameters.

Parameters

iluparam	Parameters for ILU

Author

Chensong Zhang

Date

2010/04/06

Definition at line 236 of file parameters.c.

9.63.2.7 void fasp_param_ilu_print (ILU_param * param)

Print out ILU parameters.

Parameters

param Parameters for ILU	
--------------------------	--

Author

Chensong Zhang

Date

2011/12/20

Definition at line 666 of file parameters.c.

9.63.2.8 void fasp_param_ilu_set (ILU_param * iluparam, input_param * inparam)

Set ILU_param with INPUT.

Parameters

iluparam	Parameters for ILU
inparam	Input parameters

Author

Chensong Zhang

Date

2010/04/03

Definition at line 345 of file parameters.c.

9.63.2.9 void fasp_param_init (char * inputfile, input_param * inparam, itsolver_param * itsparam, AMG_param * amgparam, ILU_param * iluparam, Schwarz_param * schparam)

Initialize parameters, global variables, etc.

Parameters

inputfile	Filename of the input file
inparam	Input parameters
itsparam	Iterative solver parameters
amgparam	AMG parameters
iluparam	ILU parameters
schparam	Schwarz parameters

Author

Chensong Zhang

Date

2010/08/12

Modified by Xiaozhe Hu (01/23/2011): initialize, then set value Modified by Chensong Zhang (09/12/2012): find a bug during debugging in VS08

Definition at line 38 of file parameters.c.

9.63.2.10 void fasp_param_input_init (input_param * inparam)

Initialize input parameters.

Parameters

inparam	Input parameters

Author

Chensong Zhang

Date

2010/03/20

Definition at line 78 of file parameters.c.

9.63.2.11 void fasp_param_prec_to_amg (AMG_param * amgparam, precond_data * pcdata)

Set AMG_param with precond_data.

Parameters

amgparam	Parameters for AMG
pcdata	Preconditioning data structure

Author

Chensong Zhang

Date

2011/01/10

Definition at line 480 of file parameters.c.

9.63.2.12 void fasp_param_prec_to_amg_bsr (AMG_param * amgparam, precond_data_bsr * pcdata)

Set AMG_param with precond_data.

Parameters

	amgparam	Parameters for AMG
Ī	pcdata	Preconditioning data structure

Author

Xiaozhe Hu

Date

02/06/2012

Definition at line 544 of file parameters.c.

9.63.2.13 void fasp_param_schwarz_init (Schwarz_param * schparam)

Initialize Schwarz parameters.

Parameters

schparam	Parameters for Schwarz method
----------	-------------------------------

Author

Xiaozhe Hu

Date

05/22/2012

Definition at line 256 of file parameters.c.

9.63.2.14 void fasp_param_schwarz_print (Schwarz_param * param)

Print out Schwarz parameters.

Parameters

param	Parameters for Schwarz

Author

Xiaozhe Hu

Date

05/22/2012

Definition at line 696 of file parameters.c.

9.63.2.15 void fasp_param_schwarz_set (Schwarz_param * schparam, input_param * inparam)

Set Schwarz_param with INPUT.

schparam	Parameters for Schwarz method
inparam	Input parameters

Author

Xiaozhe Hu

Date

05/22/2012

Definition at line 367 of file parameters.c.

9.63.2.16 void fasp_param_solver_init (itsolver_param * itsparam)

Initialize itsolver_param.

Parameters

itsparam	Parameters for iterative solvers
----------	----------------------------------

Author

Chensong Zhang

Date

2010/03/23

Definition at line 215 of file parameters.c.

9.63.2.17 void fasp_param_solver_print (itsolver_param * param)

Print out itsolver parameters.

Parameters

param	Paramters for iterative solvers
-------	---------------------------------

Author

Chensong Zhang

Date

2011/12/20

Definition at line 725 of file parameters.c.

9.63.2.18 void fasp_param_solver_set (itsolver_param * itsparam, input_param * inparam)

Set itsolver_param with INPUT.

Parameters

itsparam	Parameters for iterative solvers
inparam	Input parameters

Author

Chensong Zhang

Date

2010/03/23

Definition at line 387 of file parameters.c.

9.63.2.19 void fasp_precond_data_null (precond_data * pcdata)

Initialize precond_data.

Parameters

pcdata	Preconditioning data structure
--------	--------------------------------

Author

Chensong Zhang

Date

2010/03/23

Definition at line 416 of file parameters.c.

9.64 pbcgs.c File Reference

Krylov subspace methods - Preconditioned BiCGstab.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

• INT fasp_solver_dcsr_pbcgs (dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop type, const SHORT print level)

Preconditioned BiCGstab method for solving Au=b.

• INT fasp_solver_dbsr_pbcgs (dBSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b.

• INT fasp_solver_bdcsr_pbcgs (block_dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop type, const SHORT print level)

A preconditioned BiCGstab method for solving Au=b.

INT fasp_solver_dstr_pbcgs (dSTRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop type, const SHORT print level)

Preconditioned BiCGstab method for solving Au=b.

9.64.1 Detailed Description

Krylov subspace methods - Preconditioned BiCGstab. Abstract algorithm

PBICGStab method to solve A*x=b is to generate {x k} to approximate x

Note: We generate a series of {p_k} such that V_k=span{p_1,...,p_k}.

Step 0. Given A, b, x 0, M

Step 1. Compute residual $r_0 = b-A*x_0$ and convergence check;

Step 2. Initialization $z_0 = M^{-1}*r_0$, $p_0=z_0$;

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r k,z k,p k);
- update solution: x_{k+1} = x_k + alpha*p_k;
- · perform stagnation check;
- update residual: r_{k+1} = r_k alpha*(A*p_k);
- · perform residual check;
- obtain p_{k+1} using {p_0, p_1, ..., p_k};
- · prepare for next iteration;
- · print the result of k-th iteration; END FOR

Convergence check: norm(r)/norm(b) < tol

Stagnation check:

- IF norm(alpha*p_k)/norm(x_{k+1}) < tol_stag
 - 1. compute $r=b-A*x_{k+1}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Stag_Check) restart;
- END IF

Residual check:

- IF $norm(r_{k+1})/norm(b) < tol$
 - 1. compute the real residual $r = b-A*x \{k+1\}$;
 - 2. convergence check;

- 3. IF (not converged & restart_number < Max_Res_Check) restart;
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See spbcgs.c for a safer version

Definition in file pbcgs.c.

9.64.2 Function Documentation

9.64.2.1 INT fasp_solver_bdcsr_pbcgs (block_dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned BiCGstab method for solving Au=b.

Parameters

Α	Pointer to the coefficient matrix
b	Pointer to the dvector of right hand side
и	Pointer to the dvector of DOFs
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Xiaozhe Hu

Date

05/24/2010

Rewritten by Chensong Zhang on 04/30/2012 Modified by Feiteng Huang on 06/01/2012: fix restart param-init Modified by Chensong Zhang on 03/31/2013

Definition at line 781 of file pbcgs.c.

9.64.2.2 INT fasp_solver_dbsr_pbcgs (dBSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b.

Α	Pointer to the coefficient matrix
b	Pointer to the dvector of right hand side
и	Pointer to the dvector of DOFs
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

09/09/2009

Rewritten by Chensong Zhang on 04/30/2012 Modified by Feiteng Huang on 06/01/2012: fix restart param-init Modified by Chensong Zhang on 03/31/2013

Definition at line 435 of file pbcgs.c.

9.64.2.3 INT fasp_solver_dcsr_pbcgs (dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b.

Parameters

Α	Pointer to the coefficient matrix
b	Pointer to the dvector of right hand side
и	Pointer to the dvector of DOFs
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

09/09/2009

Rewritten by Chensong Zhang on 04/30/2012 Modified by Feiteng Huang on 06/01/2012: fix restart param-init Modified by Chensong Zhang on 03/31/2013

Definition at line 89 of file pbcgs.c.

9.64.2.4 INT fasp_solver_dstr_pbcgs (dSTRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b.

Parameters

Α	Pointer to the coefficient matrix
b	Pointer to the dvector of right hand side
и	Pointer to the dvector of DOFs
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Zhiyang Zhou

Date

04/25/2010

Rewritten by Chensong Zhang on 04/30/2012 Modified by Feiteng Huang on 06/01/2012: fix restart param-init Modified by Chensong Zhang on 03/31/2013

Definition at line 1127 of file pbcgs.c.

9.65 pbcgs_mf.c File Reference

Krylov subspace methods - Preconditioned BiCGstab (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

INT fasp_solver_pbcgs (mxv_matfree *mf, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b.

9.65.1 Detailed Description

Krylov subspace methods - Preconditioned BiCGstab (matrix free) Abstract algorithm of Krylov method

Krylov method to solve A*x=b is to generate $\{x_k\}$ to approximate x, where x_k is the optimal solution in Krylov space

$$V_k=span\{r_0,A*r_0,A^2*r_0,...,A^{k-1}*r_0\},$$

under some inner product.

For the implementation, we generate a series of {p_k} such that V_k=span{p_1,...,p_k}. Details:

Step 0. Given A, b, x_0, M

Step 1. Compute residual $r_0 = b-A*x_0$ and convergence check;

Step 2. Initialization z $0 = M^{-1}*r 0$, p 0=z 0;

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r_k,z_k,p_k);
- update solution: x_{k+1} = x_k + alpha*p_k;
- · perform stagnation check;
- update residual: r {k+1} = r k alpha*(A*p k);
- · perform residual check;
- obtain p_{k+1} using {p_0, p_1, ..., p_k};
- · prepare for next iteration;
- print the result of k-th iteration; END FOR

Convergence check is: norm(r)/norm(b) < tol

Stagnation check is like following:

- IF $norm(alpha*p_k)/norm(x_{k+1}) < tol_stag$
 - 1. compute $r=b-A*x_{k+1}$;
 - 2. convergence check;
 - 3. IF (not converged & restart number < Max Stag Check) restart;
- END IF

Residual check is like following:

- IF $norm(r_{k+1})/norm(b) < tol$
 - 1. compute the real residual $r = b-A*x \{k+1\}$;

- 2. convergence check;
- 3. IF (not converged & restart_number < Max_Res_Check) restart;
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM

Definition in file pbcgs_mf.c.

9.65.2 Function Documentation

9.65.2.1 INT fasp_solver_pbcgs (mxv_matfree * mf, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b.

Parameters

mf	Pointer to mxv_matfree: the spmv operation
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

09/09/2009

Rewritten by Chensong Zhang on 04/30/2012 Modified by Feiteng Huang on 06/01/2012: fix restart param-init Modified by Feiteng Huang on 09/26/2012, (mmatrix free)

Definition at line 91 of file pbcgs_mf.c.

9.66 pcg.c File Reference

Krylov subspace methods – Preconditioned conjugate gradient.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

 INT fasp_solver_dcsr_pcg (dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient method for solving Au=b.

 INT fasp_solver_bdcsr_pcg (block_dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient method for solving Au=b.

INT fasp_solver_dstr_pcg (dSTRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient method for solving Au=b.

9.66.1 Detailed Description

Krylov subspace methods - Preconditioned conjugate gradient. Abstract algorithm

PCG method to solve A*x=b is to generate {x_k} to approximate x

Step 0. Given A, b, x 0, M

Step 1. Compute residual $r_0 = b-A*x_0$ and convergence check;

Step 2. Initialization $z_0 = M^{(-1)}*r_0, p_0=z_0$;

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r_k,z_k,p_k);
- update solution: x_{k+1} = x_k + alpha*p_k;
- · perform stagnation check;
- update residual: r_{k+1} = r_k alpha*(A*p_k);
- · perform residual check;
- obtain p_{k+1} using {p_0, p_1, ..., p_k};
- · prepare for next iteration;
- print the result of k-th iteration; END FOR

Convergence check: norm(r)/norm(b) < tol

Stagnation check:

- IF norm(alpha*p_k)/norm(x_{k+1}) < tol_stag
 - 1. compute $r=b-A*x_{k+1}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Stag_Check) restart;
- END IF

Residual check:

• IF norm(r {k+1})/norm(b) < tol

- 1. compute the real residual $r = b-A*x_{k+1}$;
- 2. convergence check;
- 3. IF (not converged & restart_number < Max_Res_Check) restart;
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See spcg.c for a safer version

Definition in file pcg.c.

9.66.2 Function Documentation

9.66.2.1 INT fasp_solver_bdcsr_pcg (block_dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient method for solving Au=b.

Parameters

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Xiaozhe Hu

Date

05/24/2010

Modified by Chensong Zhang on 04/30/2012 Modified by Chensong Zhang on 03/28/2013 Definition at line 367 of file pcg.c.

9.66.2.2 INT fasp_solver_dcsr_pcg (dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient method for solving Au=b.

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang, Xiaozhe Hu, Shiquan Zhang

Date

05/06/2010

Modified by Chensong Zhang on 04/30/2012 Modified by Chensong Zhang on 03/28/2013 Definition at line 85 of file pcg.c.

9.66.2.3 INT fasp_solver_dstr_pcg (dSTRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient method for solving Au=b.

Parameters

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Zhiyang Zhou

Date

04/25/2010

Modified by Chensong Zhang on 04/30/2012 Modified by Chensong Zhang on 03/28/2013 Definition at line 648 of file pcg.c.

9.67 pcg_mf.c File Reference

Krylov subspace methods – Preconditioned conjugate gradient (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

INT fasp_solver_pcg (mxv_matfree *mf, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient (CG) method for solving Au=b.

9.67.1 Detailed Description

Krylov subspace methods - Preconditioned conjugate gradient (matrix free) Abstract algorithm

PCG method to solve A*x=b is to generate $\{x_k\}$ to approximate x

```
Step 0. Given A, b, x_0, M
```

Step 1. Compute residual $r_0 = b-A*x_0$ and convergence check;

```
Step 2. Initialization z_0 = M^{(-1)}*r_0, p_0=z_0;
```

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r_k,z_k,p_k);
- update solution: x_{k+1} = x_k + alpha*p_k;
- · perform stagnation check;
- update residual: r_{k+1} = r_k alpha*(A*p_k);
- · perform residual check;
- obtain p_{k+1} using {p_0, p_1, ..., p_k};
- · prepare for next iteration;
- · print the result of k-th iteration; END FOR

Convergence check is: norm(r)/norm(b) < tol

Stagnation check is like following:

- IF norm(alpha*p_k)/norm(x_{k+1}) < tol_stag
 - 1. compute $r=b-A*x \{k+1\}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Stag_Check) restart;

• END IF

Residual check is like following:

- IF $norm(r_{k+1})/norm(b) < tol$
 - 1. compute the real residual $r = b-A*x_{k+1}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Res_Check) restart;
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM

Definition in file pcg_mf.c.

9.67.2 Function Documentation

9.67.2.1 INT fasp_solver_pcg (mxv_matfree * mf, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient (CG) method for solving Au=b.

Parameters

mf	Pointer to mxv_matfree: the spmv operation
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang, Xiaozhe Hu, Shiquan Zhang

Date

05/06/2010

Modified by Chensong Zhang on 04/30/2012 Modified by Feiteng Huang on 09/19/2012, (matrix free) Definition at line 87 of file pcg_mf.c.

9.68 pgcg.c File Reference

Krylov subspace methods - Preconditioned Generalized CG.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

INT fasp_solver_dcsr_pgcg (dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned generilzed conjugate gradient (GCG) method for solving Au=b.

9.68.1 Detailed Description

Krylov subspace methods – Preconditioned Generalized CG.

Note

Refer to Concus, P. and Golub, G.H. and O'Leary, D.P. A Generalized Conjugate Gradient Method for the Numerical: Solution of Elliptic Partial Differential Equations, Computer Science Department, Stanford University, 1976

Definition in file pgcg.c.

9.68.2 Function Documentation

9.68.2.1 INT fasp_solver_dcsr_pgcg (dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned generilzed conjugate gradient (GCG) method for solving Au=b.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Xiaozhe Hu

Date

01/01/2012

Note

Not completely implemented yet! -Chensong

Modified by Chensong Zhang on 05/01/2012

Definition at line 46 of file pgcg.c.

9.69 pgcg_mf.c File Reference

Krylov subspace methods – Preconditioned Generalized CG (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver util.inl"
```

Functions

INT fasp_solver_pgcg (mxv_matfree *mf, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned generilzed conjugate gradient (GCG) method for solving Au=b.

9.69.1 Detailed Description

Krylov subspace methods – Preconditioned Generalized CG (matrix free)

Note

Refer to Concus, P. and Golub, G.H. and O'Leary, D.P. A Generalized Conjugate Gradient Method for the Numerical: Solution of Elliptic Partial Differential Equations, Computer Science Department, Stanford University, 1976

Definition in file pgcg mf.c.

9.69.2 Function Documentation

9.69.2.1 INT fasp_solver_pgcg (mxv_matfree * mf, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned generilzed conjugate gradient (GCG) method for solving Au=b.

Parameters

mf	Pointer to mxv_matfree: the spmv operation
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type – Not implemented
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Xiaozhe Hu

Date

01/01/2012

Note

Not completely implemented yet! - Chensong

Modified by Chensong Zhang on 05/01/2012 Modified by Feiteng Huang on 09/26/2012, (matrix free) Definition at line 47 of file pgcg mf.c.

9.70 pgmres.c File Reference

Krylov subspace methods - Preconditioned GMRes.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

 INT fasp_solver_dcsr_pgmres (dCSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b.

• INT fasp_solver_bdcsr_pgmres (block_dCSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop type, const SHORT print level)

Preconditioned GMRES method for solving Au=b.

 INT fasp_solver_dbsr_pgmres (dBSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level) Preconditioned GMRES method for solving Au=b.

• INT fasp_solver_dstr_pgmres (dSTRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b.

9.70.1 Detailed Description

Krylov subspace methods – Preconditioned GMRes.

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See also pvgmres.c for a variable restarting version.

See spgmres.c for a safer version

Definition in file pgmres.c.

9.70.2 Function Documentation

9.70.2.1 INT fasp_solver_bdcsr_pgmres (block_dCSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b.

Parameters

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Xiaozhe Hu

Date

05/24/2010

Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/05/2013: add stop_type and safe check

Definition at line 345 of file pgmres.c.

9.70.2.2 INT fasp_solver_dbsr_pgmres (dBSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b.

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Zhiyang Zhou

Date

2010/12/21

Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/05/2013: add stop_type and safe check

Definition at line 641 of file pgmres.c.

9.70.2.3 INT fasp_solver_dcsr_pgmres (dCSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Zhiyang Zhou

Date

2010/11/28

Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/05/2013: add stop_type and safe check Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate

Definition at line 49 of file pgmres.c.

9.70.2.4 INT fasp_solver_dstr_pgmres (dSTRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b.

Parameters

A	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Zhiyang Zhou

Date

2010/11/28

Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/05/2013: add stop_type and safe check

Definition at line 937 of file pgmres.c.

9.71 pgmres_mf.c File Reference

Krylov subspace methods – Preconditioned GMRes (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

 INT fasp_solver_pgmres (mxv_matfree *mf, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES (right preconditioned) iterative method.

9.71.1 Detailed Description

Krylov subspace methods – Preconditioned GMRes (matrix free)

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM Refer to A.H. Baker, E.R. Jessup, and Tz.V. Kolev A Simple Strategy for Varying the Restart Parameter in GMRE-S(m) Journal of Computational and Applied Mathematics, 230 (2009) pp. 751-761. UCRL-JRNL-235266.

Definition in file pgmres mf.c.

9.71.2 Function Documentation

9.71.2.1 INT fasp_solver_pgmres (mxv_matfree * mf, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES (right preconditioned) iterative method.

Parameters

mf	Pointer to mxv_matfree: the spmv operation
b	Pointer to dvector: the right hand side
Х	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type – DOES not support this parameter
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Zhiyang Zhou

Date

2010/11/28

Modified by Chensong Zhang on 05/01/2012 Modified by Feiteng Huang on 09/26/2012, (matrix free) Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate

Definition at line 51 of file pgmres mf.c.

9.72 pminres.c File Reference

Krylov subspace methods – Preconditioned minimal residual.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

 INT fasp_solver_dcsr_pminres (dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b.

 INT fasp_solver_bdcsr_pminres (block_dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b.

 INT fasp_solver_dstr_pminres (dSTRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b.

9.72.1 Detailed Description

Krylov subspace methods - Preconditioned minimal residual. Abstract algorithm of Krylov method

Krylov method to solve A*x=b is to generate {x_k} to approximate x, where x_k is the optimal solution in Krylov space

```
V k=span{r 0,A*r 0,A^2*r 0,...,A^{k-1}*r 0},
```

under some inner product.

For the implementation, we generate a series of $\{p_k\}$ such that $V_k=span\{p_1,...,p_k\}$. Details:

```
Step 0. Given A, b, x 0, M
```

Step 1. Compute residual $r_0 = b-A*x_0$ and convergence check;

```
Step 2. Initialization z 0 = M^{\uparrow} \{-1\} * r \ 0, p \ 0 = z \ 0;
```

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r k,z k,p k);
- update solution: x_{k+1} = x_k + alpha*p_k;
- · perform stagnation check;
- update residual: $r_{k+1} = r_k alpha*(A*p_k)$;
- · perform residual check;
- obtain p {k+1} using {p 0, p 1, ..., p k};
- · prepare for next iteration;
- print the result of k-th iteration; END FOR

Convergence check: norm(r)/norm(b) < tol

Stagnation check:

- IF $norm(alpha*p_k)/norm(x_{k+1}) < tol_stag$
 - 1. compute $r=b-A*x_{k+1}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Stag_Check) restart;
- END IF

Residual check:

- IF norm(r_{k+1})/norm(b) < tol
 - 1. compute the real residual $r = b-A*x_{k+1}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Res_Check) restart;
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See spminres.c for a safer version

Definition in file pminres.c.

9.72.2 Function Documentation

9.72.2.1 INT fasp_solver_bdcsr_pminres (block_dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b.

Parameters

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

05/01/2012

Note

Rewritten based on the original version by Xiaozhe Hu 05/24/2010

Modified by Chensong Zhang on 04/09/2013

Definition at line 499 of file pminres.c.

9.72.2.2 INT fasp_solver_dcsr_pminres (dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

05/01/2012

Note

Rewritten based on the original version by Shiquan Zhang 05/10/2010

Modified by Chensong Zhang on 04/09/2013

Definition at line 93 of file pminres.c.

9.72.2.3 INT fasp_solver_dstr_pminres (dSTRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b.

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/09/2013

Definition at line 901 of file pminres.c.

9.73 pminres_mf.c File Reference

Krylov subspace methods - Preconditioned minimal residual (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

• INT fasp_solver_pminres (mxv_matfree *mf, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b.

9.73.1 Detailed Description

Krylov subspace methods – Preconditioned minimal residual (matrix free) Abstract algorithm of Krylov method Krylov method to solve A*x=b is to generate $\{x_k\}$ to approximate x, where x_k is the optimal solution in Krylov space $V_k=span\{r_0,A*r_0,A^2*r_0,...,A^k\{k-1\}*r_0\}$,

under some inner product.

For the implementation, we generate a series of {p_k} such that V_k=span{p_1,...,p_k}. Details:

```
Step 0. Given A, b, x_0, M
```

Step 1. Compute residual r 0 = b-A*x 0 and convergence check;

```
Step 2. Initialization z_0 = M^{-1}*r_0, p_0=z_0;
```

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r_k,z_k,p_k);
- update solution: x_{k+1} = x_k + alpha*p_k;
- · perform stagnation check;
- update residual: r_{k+1} = r_k alpha*(A*p_k);
- · perform residual check;
- obtain p_{k+1} using {p_0, p_1, ..., p_k};
- · prepare for next iteration;
- · print the result of k-th iteration; END FOR

Convergence check is: norm(r)/norm(b) < tol

Stagnation check is like following:

- IF norm(alpha*p_k)/norm(x_{k+1}) < tol_stag
 - 1. compute $r=b-A*x \{k+1\}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Stag_Check) restart;
- END IF

Residual check is like following:

- IF $norm(r_{k+1})/norm(b) < tol$
 - 1. compute the real residual $r = b-A*x_{k+1}$;
 - 2. convergence check;
 - IF (not converged & restart_number < Max_Res_Check) restart;
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM

Definition in file pminres_mf.c.

9.73.2 Function Documentation

9.73.2.1 INT fasp_solver_pminres (mxv_matfree * mf, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b.

Parameters

mf	Pointer to mxv_matfree: the spmv operation
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Shiquan Zhang

Date

10/24/2010

Rewritten by Chensong Zhang on 05/01/2012 Modified by Feiteng Huang on 09/26/2012, (matrix free) Definition at line 90 of file pminres_mf.c.

9.74 precond_bsr.c File Reference

Preconditioners for dBSRmat matrices.

```
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void fasp_precond_dbsr_diag (REAL *r, REAL *z, void *data)

Diagonal preconditioner z=inv(D)*r.

void fasp_precond_dbsr_diag_nc2 (REAL *r, REAL *z, void *data)

Diagonal preconditioner z=inv(D)*r.

void fasp_precond_dbsr_diag_nc3 (REAL *r, REAL *z, void *data)

Diagonal preconditioner z=inv(D)*r.

void fasp_precond_dbsr_diag_nc5 (REAL *r, REAL *z, void *data)

Diagonal preconditioner z=inv(D)*r.

void fasp_precond_dbsr_diag_nc7 (REAL *r, REAL *z, void *data)

Diagonal preconditioner z=inv(D)*r.

void fasp_precond_dbsr_ilu (REAL *r, REAL *z, void *data)

ILU preconditioner.

void fasp_precond_dbsr_amg (REAL *r, REAL *z, void *data)

AMG preconditioner.

void fasp_precond_dbsr_nl_amli (REAL *r, REAL *z, void *data)

Nonliear AMLI-cycle AMG preconditioner.

9.74.1 Detailed Description

Preconditioners for dBSRmat matrices.

Definition in file precond_bsr.c.

9.74.2 Function Documentation

9.74.2.1 void fasp_precond_dbsr_amg (REAL * r, REAL * z, void * data)

AMG preconditioner.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Xiaozhe Hu

Date

08/07/2011

Definition at line 561 of file precond_bsr.c.

9.74.2.2 void fasp_precond_dbsr_diag (REAL * r, REAL * z, void * data)

Diagonal preconditioner z=inv(D)*r.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Zhou Zhiyang, Xiaozhe Hu

Date

10/26/2010

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/24/2012

Note

Works for general nb (Xiaozhe)

Definition at line 35 of file precond_bsr.c.

9.74.2.3 void fasp_precond_dbsr_diag_nc2 (REAL * r, REAL * z, void * data)

Diagonal preconditioner z=inv(D)*r.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Zhou Zhiyang, Xiaozhe Hu

Date

11/18/2011

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/24/2012

Note

Works for 2-component (Xiaozhe)

Definition at line 109 of file precond_bsr.c.

9.74.2.4 void fasp_precond_dbsr_diag_nc3 (REAL * r, REAL * z, void * data)

Diagonal preconditioner z=inv(D)*r.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Zhou Zhiyang, Xiaozhe Hu

Date

01/06/2011

Modified by Chunsheng Feng Xiaoqiang Yue

Date

05/24/2012

Note

Works for 3-component (Xiaozhe)

Definition at line 159 of file precond_bsr.c.

9.74.2.5 void fasp_precond_dbsr_diag_nc5 (REAL * r, REAL * z, void * data)

Diagonal preconditioner z=inv(D)*r.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Zhou Zhiyang, Xiaozhe Hu

Date

01/06/2011

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/24/2012

Note

Works for 5-component (Xiaozhe)

Definition at line 209 of file precond_bsr.c.

9.74.2.6 void fasp_precond_dbsr_diag_nc7 (REAL * r, REAL * z, void * data)

Diagonal preconditioner z=inv(D)*r.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Zhou Zhiyang, Xiaozhe Hu

Date

01/06/2011

Modified by Chunsheng Feng Xiaoqiang Yue

Date

05/24/2012

Note

Works for 7-component (Xiaozhe)

Definition at line 258 of file precond_bsr.c.

9.74.2.7 void fasp_precond_dbsr_ilu (REAL * r, REAL * z, void * data)

ILU preconditioner.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Shiquan Zhang

Date

11/09/2010

Note

Works for general nb (Xiaozhe)

Definition at line 304 of file precond_bsr.c.

9.74.2.8 void fasp_precond_dbsr_nl_amli (REAL * r, REAL * z, void * data)

Nonliear AMLI-cycle AMG preconditioner.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Xiaozhe Hu

Date

02/06/2012

Definition at line 604 of file precond_bsr.c.

9.75 precond_csr.c File Reference

Preconditioners for dCSRmat matrices.

```
#include "fasp.h"
#include "fasp_functs.h"
#include "forts_ns.h"
```

Functions

 precond * fasp_precond_setup (SHORT precond_type, AMG_param *amgparam, ILU_param *iluparam, dCS-Rmat *A)

Setup preconditioner interface for iterative methods.

void fasp_precond_diag (REAL *r, REAL *z, void *data)

Diagonal preconditioner z=inv(D)*r.

void fasp_precond_ilu (REAL *r, REAL *z, void *data)

ILU preconditioner.

void fasp_precond_ilu_forward (REAL *r, REAL *z, void *data)

ILU preconditioner: only forwear sweep.

void fasp precond ilu backward (REAL *r, REAL *z, void *data)

ILU preconditioner: only backward sweep.

void fasp_precond_schwarz (REAL *r, REAL *z, void *data)

get z from r by schwarz

void fasp_precond_amg (REAL *r, REAL *z, void *data)

AMG preconditioner.

void fasp_precond_famg (REAL *r, REAL *z, void *data)

Full AMG perconditioner.

void fasp_precond_amli (REAL *r, REAL *z, void *data)

AMLI AMG preconditioner.

void fasp_precond_nl_amli (REAL *r, REAL *z, void *data)

Nonliear AMLI AMG preconditioner.

void fasp_precond_free (SHORT precond_type, precond *pc)

free preconditioner

9.75.1 Detailed Description

Preconditioners for dCSRmat matrices.

Definition in file precond_csr.c.

9.75.2 Function Documentation

9.75.2.1 void fasp_precond_amg (REAL * r, REAL * z, void * data)

AMG preconditioner.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Chensong Zhang

Date

04/06/2010

Definition at line 417 of file precond csr.c.

9.75.2.2 void fasp_precond_amli (REAL * r, REAL * z, void * data)

AMLI AMG preconditioner.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Xiaozhe Hu

Date

01/23/2011

Definition at line 488 of file precond_csr.c.

9.75.2.3 void fasp_precond_diag (REAL * r, REAL * z, void * data)

Diagonal preconditioner z=inv(D)*r.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Chensong Zhang

Date

04/06/2010

Definition at line 165 of file precond_csr.c.

9.75.2.4 void fasp_precond_famg (REAL * r, REAL * z, void * data)

Full AMG perconditioner.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Xiaozhe Hu

Date

02/27/2011

Definition at line 455 of file precond_csr.c.

9.75.2.5 void fasp_precond_free (SHORT precond_type, precond * pc)

free preconditioner

Parameters

precond_type	Preconditioner type
* <i>pc</i>	precondition data & fct

Returns

void

Author

Feiteng Huang

Date

12/24/2012

Definition at line 557 of file precond_csr.c.

9.75.2.6 void fasp_precond_ilu (REAL * r, REAL * z, void * data)

ILU preconditioner.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Shiquan Zhang

Date

04/06/2010

Definition at line 191 of file precond_csr.c.

9.75.2.7 void fasp_precond_ilu_backward (REAL * r, REAL * z, void * data)

ILU preconditioner: only backward sweep.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Xiaozhe Hu, Shiquan Zhang

Date

04/06/2010

Definition at line 313 of file precond_csr.c.

9.75.2.8 void fasp_precond_ilu_forward (REAL * r, REAL * z, void * data)

ILU preconditioner: only forwear sweep.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Xiaozhe Hu, Shiquang Zhang

Date

04/06/2010

Definition at line 260 of file precond_csr.c.

9.75.2.9 void fasp_precond_nl_amli (REAL * r, REAL * z, void * data)

Nonliear AMLI AMG preconditioner.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Xiaozhe Hu

Date

04/25/2011

Definition at line 521 of file precond_csr.c.

9.75.2.10 void fasp_precond_schwarz (REAL * r, REAL * z, void * data) get z from r by schwarz

Parameters

*1	pointer to residual
*Z	pointer to preconditioned residual
*data	pointer to precondition data

Author

Xiaozhe Hu

Date

03/22/2010

Definition at line 363 of file precond_csr.c.

9.75.2.11 precond * fasp_precond_setup (SHORT precond_type, AMG_param * amgparam, ILU_param * iluparam, dCSRmat * A)

Setup preconditioner interface for iterative methods.

Parameters

precond_type	Preconditioner type
*amgparam	AMG parameters
*iluparam	ILU parameters
*A	Pointer to coefficient matrix

Returns

Pointer to preconditioner

Author

Feiteng Huang

Date

05/18/2009

Definition at line 30 of file precond_csr.c.

9.76 precond_str.c File Reference

Preconditioners for dSTRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void fasp_precond_dstr_diag (REAL *r, REAL *z, void *data)

Diagonal preconditioner z=inv(D)*r.

void fasp_precond_dstr_ilu0 (REAL *r, REAL *z, void *data)

Preconditioning using STR_ILU(0) decomposition.

void fasp precond dstr ilu1 (REAL *r, REAL *z, void *data)

Preconditioning using STR_ILU(1) decomposition.

void fasp_precond_dstr_ilu0_forward (REAL *r, REAL *z, void *data)

Preconditioning using $STR_ILU(0)$ decomposition: Lz = r.

void fasp_precond_dstr_ilu0_backward (REAL *r, REAL *z, void *data)

Preconditioning using $STR_ILU(0)$ decomposition: Uz = r.

void fasp precond dstr ilu1 forward (REAL *r, REAL *z, void *data)

Preconditioning using $STR_ILU(1)$ decomposition: Lz = r.

void fasp precond dstr ilu1 backward (REAL *r, REAL *z, void *data)

Preconditioning using STR_ILU(1) decomposition: Uz = r.

void fasp_precond_dstr_blockgs (REAL *r, REAL *z, void *data)

CPR-type preconditioner (STR format)

9.76.1 Detailed Description

Preconditioners for dSTRmat matrices.

Definition in file precond_str.c.

9.76.2 Function Documentation

9.76.2.1 void fasp_precond_dstr_blockgs (REAL * r, REAL * z, void * data)

CPR-type preconditioner (STR format)

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Shiquan Zhang

Date

10/17/2010

Definition at line 1707 of file precond_str.c.

9.76.2.2 void fasp_precond_dstr_diag (REAL * r, REAL * z, void * data)

Diagonal preconditioner z=inv(D)*r.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Shiquan Zhang

Date

04/06/2010

Definition at line 27 of file precond_str.c.

9.76.2.3 void fasp_precond_dstr_ilu0 (REAL * r, REAL * z, void * data)

Preconditioning using STR_ILU(0) decomposition.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Shiquan Zhang

Date

04/21/2010

Definition at line 55 of file precond str.c.

9.76.2.4 void fasp_precond_dstr_ilu0_backward (REAL * r, REAL * z, void * data)

Preconditioning using $STR_ILU(0)$ decomposition: Uz = r.

Parameters

	r	Pointer to the vector needs preconditioning
	Z	Pointer to preconditioned vector
ĺ	data	Pointer to precondition data

Author

Shiquan Zhang

Date

06/07/2010

Definition at line 979 of file precond_str.c.

9.76.2.5 void fasp_precond_dstr_ilu0_forward (REAL * r, REAL * z, void * data)

Preconditioning using $STR_ILU(0)$ decomposition: Lz = r.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Shiquan Zhang

Date

06/07/2010

Definition at line 816 of file precond_str.c.

9.76.2.6 void fasp_precond_dstr_ilu1 (REAL * r, REAL * z, void * data)

Preconditioning using STR_ILU(1) decomposition.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Shiquan Zhang

Date

04/21/2010

Definition at line 337 of file precond str.c.

9.76.2.7 void fasp_precond_dstr_ilu1_backward (REAL * r, REAL * z, void * data)

Preconditioning using $STR_ILU(1)$ decomposition: Uz = r.

Parameters

	r	Pointer to the vector needs preconditioning
	Z	Pointer to preconditioned vector
I	data	Pointer to precondition data

Author

Shiquan Zhang

Date

04/21/2010

Definition at line 1426 of file precond_str.c.

9.76.2.8 void fasp_precond_dstr_ilu1_forward (REAL * r, REAL * z, void * data)

Preconditioning using $STR_ILU(1)$ decomposition: Lz = r.

Parameters

r	Pointer to the vector needs preconditioning
Z	Pointer to preconditioned vector
data	Pointer to precondition data

Author

Shiquan Zhang

Date

04/21/2010

Definition at line 1160 of file precond_str.c.

9.77 pvfgmres.c File Reference

Krylov subspace methods – Preconditioned variable-restarting flexible GMRes.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

 INT fasp_solver_dcsr_pvfgmres (dCSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PFGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration and flexible preconditioner can be used.

 INT fasp_solver_dbsr_pvfgmres (dBSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PFGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration and flexible preconditioner can be used.

9.77.1 Detailed Description

Krylov subspace methods – Preconditioned variable-restarting flexible GMRes.

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM
Refer to A.H. Baker, E.R. Jessup, and Tz.V. Kolev A Simple Strategy for Varying the Restart Parameter in GMRE-S(m) Journal of Computational and Applied Mathematics, 230 (2009) pp. 751-761. UCRL-JRNL-235266.
This file is modifed from pvgmres.c

Definition in file pvfgmres.c.

9.77.2 Function Documentation

9.77.2.1 INT fasp_solver_dbsr_pvfgmres (dBSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PFGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration and flexible preconditioner can be used.

Parameters

Pointer to dCSRmat: the coefficient matrix
Pointer to dvector: the right hand side
Pointer to dvector: the unknowns
Pointer to precond: the structure of precondition
Tolerance for stopping
Maximal number of iterations
Restarting steps
Stopping criteria type – DOES not support this parameter
How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Xiaozhe Hu

Date

02/05/2012

Modified by Chensong Zhang on 05/01/2012

Definition at line 371 of file pvfgmres.c.

9.77.2.2 INT fasp_solver_dcsr_pvfgmres (dCSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PFGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration and flexible preconditioner can be used.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type – DOES not support this parameter
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Xiaozhe Hu

Date

01/04/2012

Modified by Chensong Zhang on 05/01/2012 Modified by Chunsheng Feng on 07/22/2013: Add adaptive memory allocate

Definition at line 54 of file pvfgmres.c.

9.78 pvfgmres_mf.c File Reference

Krylov subspace methods – Preconditioned variable-restarting flexible GMRes (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

 INT fasp_solver_pvfgmres (mxv_matfree *mf, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop type, const SHORT print level)

Solve "Ax=b" using PFGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration and flexible preconditioner can be used.

9.78.1 Detailed Description

Krylov subspace methods - Preconditioned variable-restarting flexible GMRes (matrix free)

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM Refer to A.H. Baker, E.R. Jessup, and Tz.V. Kolev A Simple Strategy for Varying the Restart Parameter in GMRE-S(m) Journal of Computational and Applied Mathematics, 230 (2009) pp. 751-761. UCRL-JRNL-235266. This file is modifed from pvgmres.c

Definition in file pvfgmres_mf.c.

9.78.2 Function Documentation

9.78.2.1 INT fasp_solver_pvfgmres (mxv_matfree * mf, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PFGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration and flexible preconditioner can be used.

Parameters

Pointer to mxv_matfree: the spmv operation
Pointer to dvector: the right hand side
Pointer to dvector: the unknowns
Pointer to precond: the structure of precondition
Tolerance for stopping
Maximal number of iterations
Restarting steps
Stopping criteria type – DOES not support this parameter
How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Xiaozhe Hu

Date

01/04/2012

Modified by Chensong Zhang on 05/01/2012 Modified by Feiteng Huang on 09/26/2012, (matrix free) Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate

Definition at line 56 of file pyfgmres mf.c.

9.79 pvgmres.c File Reference

Krylov subspace methods - Preconditioned variable-restart GMRes.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

 INT fasp_solver_dcsr_pvgmres (dCSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

• INT fasp_solver_bdcsr_pvgmres (block_dCSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop type, const SHORT print level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

 INT fasp_solver_dbsr_pvgmres (dBSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level) Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

 INT fasp_solver_dstr_pvgmres (dSTRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

9.79.1 Detailed Description

Krylov subspace methods - Preconditioned variable-restart GMRes.

Note

Refer to A.H. Baker, E.R. Jessup, and Tz.V. Kolev A Simple Strategy for Varying the Restart Parameter in GMRE-S(m) Journal of Computational and Applied Mathematics, 230 (2009) pp. 751-761. UCRL-JRNL-235266. See spvgmres.c for a safer version

Definition in file pvgmres.c.

9.79.2 Function Documentation

9.79.2.1 INT fasp_solver_bdcsr_pvgmres (block_dCSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/05/2013

Definition at line 384 of file pygmres.c.

9.79.2.2 INT fasp_solver_dbsr_pvgmres (dBSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Zhiyang Zhou

Date

12/21/2011

Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/06/2013: Add stop type support Definition at line 719 of file pygmres.c.

9.79.2.3 INT fasp_solver_dcsr_pvgmres (dCSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Zhiyang Zhou

Date

2010/12/14

Modified by Chensong Zhang on 12/13/2011 Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/06/2013: Add stop type support Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate Definition at line 52 of file pygmres.c.

9.79.2.4 INT fasp_solver_dstr_pvgmres (dSTRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Zhiyang Zhou

Date

2010/12/14

Modified by Chensong Zhang on 05/01/2012 Modified by Chensong Zhang on 04/06/2013: Add stop type support Definition at line 1054 of file pygmres.c.

9.80 pvgmres_mf.c File Reference

Krylov subspace methods – Preconditioned variable-restarting GMRes (matrix free)

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

 INT fasp_solver_pvgmres (mxv_matfree *mf, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

9.80.1 Detailed Description

Krylov subspace methods – Preconditioned variable-restarting GMRes (matrix free)

Note

Refer to A.H. Baker, E.R. Jessup, and Tz.V. Kolev A Simple Strategy for Varying the Restart Parameter in GMRE-S(m) Journal of Computational and Applied Mathematics, 230 (2009) pp. 751-761. UCRL-JRNL-235266.

Definition in file pvgmres_mf.c.

9.80.2 Function Documentation

9.80.2.1 INT fasp_solver_pvgmres (mxv_matfree * mf, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

Parameters

mf	Pointer to mxv_matfree: the spmv operation
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to precond: the structure of precondition
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type – DOES not support this parameter
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Zhiyang Zhou

Date

2010/12/14

Modified by Chensong Zhang on 12/13/2011 Modified by Chensong Zhang on 05/01/2012 Modified by Feiteng Huang on 09/26/2012, (matrix free) Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate

Definition at line 54 of file pygmres mf.c.

9.81 quadrature.c File Reference

Quadrature rules.

```
#include <stdio.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void fasp_quad2d (INT num_qp, INT ncoor, REAL(*quad)[3])

Initialize Lagrange quadrature points and weights.

void fasp_gauss2d (INT num_qp, INT ncoor, REAL(*gauss)[3])

Initialize Gauss quadrature points and weights.

9.81.1 Detailed Description

Quadrature rules.

Definition in file quadrature.c.

9.81.2 Function Documentation

9.81.2.1 void fasp_gauss2d (INT num_qp, INT ncoor, REAL(*) gauss[3])

Initialize Gauss quadrature points and weights.

Parameters

num_qp	Number of quadrature points
ncoor	Dimension of space
gauss	Quadrature points and weight

Author

Xuehai Huang, Chensong Zhang, Ludmil Zikatanov

Date

10/21/2008

Note

gauss[*][0] - quad point x in ref coor <math>gauss[*][1] - quad point y in ref coor <math>gauss[*][2] - quad weight

Definition at line 210 of file quadrature.c.

9.81.2.2 void fasp_quad2d (INT num_qp, INT ncoor, REAL(*) quad[3])

Initialize Lagrange quadrature points and weights.

Parameters

num_qp	Number of quadrature points
ncoor	Dimension of space
quad	Quadrature points and weights

Author

Xuehai Huang, Chensong Zhang, Ludmil Zikatanov

Date

10/21/2008

Note

quad[*][0] - quad point x in ref coor quad[*][1] - quad point y in ref coor quad[*][2] - quad weight

Definition at line 31 of file quadrature.c.

9.82 rap.c File Reference

R*A*P driver.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

```
    dCSRmat fasp_blas_dcsr_rap2 (INT *ir, INT *jr, REAL *r, INT *ia, INT *ja, REAL *a, INT *ipt, INT *jpt, REAL *pt, INT n, INT nc, INT *maxrpout, INT *ipin, INT *jpin)
    Compute R*A*P.
```

9.82.1 Detailed Description

R*A*P driver.

C-version by Ludmil Zikatanov 2010-04-08

tested 2010-04-08

Definition in file rap.c.

9.82.2 Function Documentation

```
9.82.2.1 dCSRmat fasp_blas_dcsr_rap2 ( INT * ir, INT * jr, REAL * r, INT * ia, INT * ja, REAL * a, INT * ipt, INT * jpt, REAL * pt, INT n, INT nc, INT * maxrpout, INT * ipin, INT * jpin )
```

Compute R*A*P.

Author

Ludmil Zikatanov

Date

04/08/2010

Note

It uses dCSRmat only. The functions called from here are in sparse util.c

Definition at line 33 of file rap.c.

9.83 schwarz.f File Reference

Schwarz smoothers.

Functions/Subroutines

- subroutine cut0 (n, ia, ja, a, iaw, jaw, jblk, iblk, nblk, lwork1, lwork2, lwork3, msize)
- subroutine chsize (a, b, tol, imin)
- subroutine **shift** (nxadj, nadj, n)
- subroutine dfs (n, ia, ja, nblk, iblk, jblk, lowlink, iedge, numb)
- subroutine **permat** (iord, ia, ja, an, n, m, iat, jat, ant)
- subroutine pervec (iord, u1, u2, n)
- subroutine **perback** (iord, u1, u2, n)
- subroutine **perm0** (iord, ia, ja, an, n, m, iat, jat, ant)
- subroutine icopyv (iu, iv, n)
- subroutine mxfrm2 (n, ia, ja, nblk, iblock, jblock, mask, maxa, memt, maxbs)
- subroutine **sky2ns** (n, ia, ja, a, nblk, iblock, jblock, mask, maxa, au, al)
- subroutine **fbgs2ns** (n, ia, ja, a, x, b, nblk, iblock, jblock, mask, maxa, au, al, rhsloc, memt)
- subroutine **bbgs2ns** (n, ia, ja, a, x, b, nblk, iblock, jblock, mask, maxa, au, al, rhsloc, memt)
- subroutine doluns (au, al, maxa, nn)
- subroutine **sluns** (au, al, v, maxa, nn)
- subroutine dolu (a, maxa, nn)
- subroutine siviu (a, v, maxa, nn)
- subroutine ijacrs (In, ia, ja, a, n, nnz, ir, ic, aij)
- subroutine sympat (In, ia, ja, n, ir, ic, aij)
- subroutine levels (inroot, ia, ja, mask, nlvl, iblock, jblock, maxlev)

9.83.1 Detailed Description

Schwarz smoothers.

Author

Ludmil Zikatanov

Date

01/01/2007

Note

These routines are part of the matching MG method

Definition in file schwarz.f.

9.84 schwarz_setup.c File Reference

Setup phase for the Schwarz methods.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "forts_ns.h"
```

Functions

INT fasp_schwarz_setup (Schwarz_data *schwarz, INT mmsize, INT maxlev, INT schwarz_type)
 Setup phase for the Schwarz methods.

9.84.1 Detailed Description

Setup phase for the Schwarz methods.

Definition in file schwarz_setup.c.

9.84.2 Function Documentation

 $9.84.2.1 \quad \textbf{INT fasp_schwarz_setup (Schwarz_data} * \textit{schwarz, INT mmsize, INT maxlev, INT schwarz_type)}$

Setup phase for the Schwarz methods.

Parameters

sch	hwarz	Pointer to the showarz data
mı	msize	Max block size
m	axlev	Max number of levels
schwarz_	_type	Type of the Schwarz method

Returns

SUCCESS if succeed

```
Author
```

Ludmil, Xiaozhe Hu

Date

03/22/2011

Modified by Chunsheng Feng, Zheng Li on 08/28/2012 find the blocks

LU decomposition of blocks

return

Definition at line 35 of file schwarz_setup.c.

9.85 smat.c File Reference

Simple operations for *small* full matrices in row-major format.

```
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void fasp blas smat inv nc2 (REAL *a)

Compute the inverse matrix of a 2*2 full matrix A (in place)

void fasp_blas_smat_inv_nc3 (REAL *a)

Compute the inverse matrix of a 3*3 full matrix A (in place)

void fasp_blas_smat_inv_nc4 (REAL *a)

Compute the inverse matrix of a 4*4 full matrix A (in place)

void fasp_blas_smat_inv_nc5 (REAL *a)

Compute the inverse matrix of a 5*5 full matrix A (in place)

void fasp_blas_smat_inv_nc7 (REAL *a)

Compute the inverse matrix of a 7*7 matrix a.

INT fasp_blas_smat_inv (REAL *a, const INT n)

Compute the inverse matrix of a small full matrix a.

void fasp_iden_free (idenmat *A)

Free idenmat sparse matrix data memeory space.

• void fasp_smat_identity_nc2 (REAL *a)

Set a 2*2 full matrix to be a identity.

void fasp_smat_identity_nc3 (REAL *a)

Set a 3*3 full matrix to be a identity.

void fasp_smat_identity_nc5 (REAL *a)

Set a 5*5 full matrix to be a identity.

void fasp_smat_identity_nc7 (REAL *a)

Set a 7*7 full matrix to be a identity.

void fasp_smat_identity (REAL *a, INT n, INT n2)

Set a n*n full matrix to be a identity.

9.85 smat.c File Reference 323

9.85.1 Detailed Description

Simple operations for small full matrices in row-major format.

Definition in file smat.c.

9.85.2 Function Documentation

9.85.2.1 INT fasp_blas_smat_inv (REAL * a, const INT n)

Compute the inverse matrix of a small full matrix a.

Parameters

а	Pointer to the REAL array which stands a n∗n matrix
n	Dimension of the matrix

Author

Xiaozhe Hu, Shiquan Zhang

Date

04/21/2010

Definition at line 392 of file smat.c.

9.85.2.2 void fasp_blas_smat_inv_nc2 (REAL * a)

Compute the inverse matrix of a 2*2 full matrix A (in place)

Parameters

a Pointer to the REAL array which stands a 2*2 matrix

Author

Xiaozhe Hu

Date

18/11/2011

Definition at line 23 of file smat.c.

9.85.2.3 void fasp_blas_smat_inv_nc3 (REAL *a)

Compute the inverse matrix of a 3*3 full matrix A (in place)

Parameters

a Pointer to the REAL array which stands a 3*3 matrix

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 59 of file smat.c.

9.85.2.4 void fasp_blas_smat_inv_nc4 (REAL * a)

Compute the inverse matrix of a 4*4 full matrix A (in place)

Parameters

a Pointer to the REAL array which stands a 4*4 matrix

Author

Xiaozhe Hu

Date

01/12/2013

Definition at line 102 of file smat.c.

9.85.2.5 void fasp_blas_smat_inv_nc5 (REAL * a)

Compute the inverse matrix of a 5*5 full matrix A (in place)

Parameters

a Pointer to the REAL array which stands a 5*5 matrix

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 160 of file smat.c.

9.85.2.6 void fasp_blas_smat_inv_nc7 (REAL * a)

Compute the inverse matrix of a 7*7 matrix a.

9.85 smat.c File Reference 325

Parameters

a Pointer to the REAL array which stands a 7*7 matrix		
	а	Pointer to the REAL array which stands a 7*7 matrix

Note

This is NOT implemented yet!

Author

Xiaozhe Hu, Shiquan Zhang

Date

05/01/2010

Definition at line 376 of file smat.c.

9.85.2.7 void fasp_iden_free (idenmat * A)

Free idenmat sparse matrix data memeory space.

Parameters

Α	Pointer to the idenmat matrix
---	-------------------------------

Author

Chensong Zhang

Date

2010/04/03

Definition at line 481 of file smat.c.

9.85.2.8 void fasp_smat_identity (REAL * a, INT n, INT n2)

Set a n*n full matrix to be a identity.

Parameters

а	Pointer to the REAL vector which stands for a n∗n full matrix
n	Size of full matrix
n2	Length of the REAL vector which stores the n∗n full matrix

Author

Xiaozhe Hu

Date

2010/12/25

Definition at line 581 of file smat.c.

9.85.2.9 void fasp_smat_identity_nc2 (REAL *a)

Set a 2*2 full matrix to be a identity.

9.85 smat.c File Reference 327

Parameters

a Pointer to the REAL vector which stands for a 2*2 full matrix

Author

Xiaozhe Hu

Date

2011/11/18

Definition at line 501 of file smat.c.

9.85.2.10 void fasp_smat_identity_nc3 (REAL * a)

Set a 3*3 full matrix to be a identity.

Parameters

a Pointer to the REAL vector which stands for a 3*3 full matrix

Author

Xiaozhe Hu

Date

2010/12/25

Definition at line 518 of file smat.c.

9.85.2.11 void fasp_smat_identity_nc5 (REAL *a)

Set a 5*5 full matrix to be a identity.

Parameters

a Pointer to the REAL vector which stands for a 5*5 full matrix

Author

Xiaozhe Hu

Date

2010/12/25

Definition at line 535 of file smat.c.

9.85.2.12 void fasp_smat_identity_nc7 (REAL *a)

Set a 7*7 full matrix to be a identity.

Parameters

a Pointer to the REAL vector which stands for a 7*7 full matrix

Author

Xiaozhe Hu

Date

2010/12/25

Definition at line 556 of file smat.c.

9.86 smoother bsr.c File Reference

Smoothers for dBSRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

- void fasp_smoother_dbsr_jacobi (dBSRmat *A, dvector *b, dvector *u)
 Jacobi relaxation.
- void fasp_smoother_dbsr_jacobi_setup (dBSRmat *A, dvector *b, dvector *u, REAL *diaginv)

 Setup for jacobi relaxation, fetch the diagonal sub-block matrixes and make them inverse first.
- void fasp_smoother_dbsr_jacobi1 (dBSRmat *A, dvector *b, dvector *u, REAL *diaginv)
 Jacobi relaxation.
- void fasp_smoother_dbsr_gs (dBSRmat *A, dvector *b, dvector *u, INT order, INT *mark)

 *Gauss-Seidel relaxation.
- void fasp_smoother_dbsr_gs1 (dBSRmat *A, dvector *b, dvector *u, INT order, INT *mark, REAL *diaginv) Gauss-Seidel relaxation.
- void fasp_smoother_dbsr_gs_ascend (dBSRmat *A, dvector *b, dvector *u, REAL *diaginv)

Gauss-Seidel relaxation in the ascending order.

- void fasp_smoother_dbsr_gs_descend (dBSRmat *A, dvector *b, dvector *u, REAL *diaginv)
 Gauss-Seidel relaxation in the descending order.
- void fasp_smoother_dbsr_gs_order1 (dBSRmat *A, dvector *b, dvector *u, REAL *diaginv, INT *mark)
 Gauss-Seidel relaxation in the user-defined order.
- void fasp_smoother_dbsr_gs_order2 (dBSRmat *A, dvector *b, dvector *u, INT *mark, REAL *work)
- Gauss-Seidel relaxation in the user-defined order.

 void fasp_smoother_dbsr_sor (dBSRmat *A, dvector *b, dvector *u, INT order, INT *mark, REAL weight)
- void fasp_smoother_dbsr_sor1 (dBSRmat *A, dvector *b, dvector *u, INT order, INT *mark, REAL *diaginv, REAL weight)

SOR relaxation.

SOR relaxation.

void fasp smoother dbsr sor ascend (dBSRmat *A, dvector *b, dvector *u, REAL *diaginv, REAL weight)

SOR relaxation in the ascending order.

- void fasp_smoother_dbsr_sor_descend (dBSRmat *A, dvector *b, dvector *u, REAL *diaginv, REAL weight) SOR relaxation in the descending order.
- void fasp_smoother_dbsr_sor_order (dBSRmat *A, dvector *b, dvector *u, REAL *diaginv, INT *mark, REAL weight)

SOR relaxation in the user-defined order.

• void fasp_smoother_dbsr_ilu (dBSRmat *A, dvector *b, dvector *x, void *data)

ILU method as the smoother in solving Au=b with multigrid method.

9.86.1 Detailed Description

Smoothers for dBSRmat matrices.

Definition in file smoother bsr.c.

9.86.2 Function Documentation

9.86.2.1 void fasp_smoother_dbsr_gs (dBSRmat * A, dvector * b, dvector * u, INT order, INT * mark)

Gauss-Seidel relaxation.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending order DES-
	CEND 21: in descending order If mark != NULL: in the user-defined order
mark	Pointer to NULL or to the user-defined ordering

Author

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 08/03/2012

Definition at line 415 of file smoother_bsr.c.

9.86.2.2 void fasp_smoother_dbsr_gs1 (dBSRmat * A, dvector * b, dvector * u, INT order, INT * mark, REAL * diaginv)

Gauss-Seidel relaxation.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending order DES-
	CEND 21: in descending order If mark != NULL: in the user-defined order
mark	Pointer to NULL or to the user-defined ordering
diaginv	Inverses for all the diagonal blocks of A

Author

Zhiyang Zhou

Date

2010/10/25

Definition at line 535 of file smoother_bsr.c.

9.86.2.3 void fasp_smoother_dbsr_gs_ascend (dBSRmat * A, dvector * b, dvector * u, REAL * diaginv)

Gauss-Seidel relaxation in the ascending order.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
diaginv	Inverses for all the diagonal blocks of A

Author

Zhiyang Zhou

Date

2010/10/25

Definition at line 572 of file smoother_bsr.c.

9.86.2.4 void fasp_smoother_dbsr_gs_descend (dBSRmat * A, dvector * b, dvector * u, REAL * diaginv)

Gauss-Seidel relaxation in the descending order.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)

diaginv	Inverses for all the diagonal blocks of A

Author

Zhiyang Zhou

Date

2010/10/25

Definition at line 642 of file smoother_bsr.c.

9.86.2.5 void fasp_smoother_dbsr_gs_order1 (dBSRmat * A, dvector * b, dvector * u, REAL * diaginv, INT * mark)

Gauss-Seidel relaxation in the user-defined order.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
diaginv	Inverses for all the diagonal blocks of A
mark	Pointer to the user-defined ordering

Author

Zhiyang Zhou

Date

2010/10/25

Definition at line 713 of file smoother_bsr.c.

9.86.2.6 void fasp_smoother_dbsr_gs_order2 (dBSRmat * A, dvector * b, dvector * u, INT * mark, REAL * work)

Gauss-Seidel relaxation in the user-defined order.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
mark	Pointer to the user-defined ordering
work	Work temp array

Author

Zhiyang Zhou

Date

2010/11/08

Note

The only difference between the functions 'fasp_smoother_dbsr_gs_order2' and 'fasp_smoother_dbsr_gs_order1' lies in that we don't have to multiply by the inverses of the diagonal blocks in each ROW since matrix A has been such scaled that all the diagonal blocks become identity matrices.

Definition at line 791 of file smoother_bsr.c.

```
9.86.2.7 void fasp_smoother_dbsr_ilu ( dBSRmat * A, dvector * b, dvector * x, void * data )
```

ILU method as the smoother in solving Au=b with multigrid method.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
data	Pointer to user defined data

Author

Zhiyang Zhou

Date

2010/10/25

form residual zr = b - A x

solve LU z=zr

X=X+Z

Definition at line 1424 of file smoother_bsr.c.

9.86.2.8 void fasp_smoother_dbsr_jacobi (dBSRmat * A, dvector * b, dvector * u)

Jacobi relaxation.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)

Author

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 08/02/2012

Definition at line 35 of file smoother_bsr.c.

9.86.2.9 void fasp_smoother_dbsr_jacobi1 (dBSRmat*A, dvector*b, dvector*u, REAL*diaginv) Jacobi relaxation.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
diaginv	Inverses for all the diagonal blocks of A

Author

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 08/03/2012

Definition at line 259 of file smoother_bsr.c.

9.86.2.10 void fasp_smoother_dbsr_jacobi_setup (dBSRmat * A, dvector * b, dvector * u, REAL * diaginv)

Setup for jacobi relaxation, fetch the diagonal sub-block matrixes and make them inverse first.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
diaginv	Inverse of the diagonal entries

Author

Zhiyang Zhou

Date

10/25/2010

Modified by Chunsheng Feng, Zheng Li on 08/02/2012

Definition at line 150 of file smoother_bsr.c.

9.86.2.11 void fasp_smoother_dbsr_sor (dBSRmat * A, dvector * b, dvector * u, INT order, INT * mark, REAL weight)

SOR relaxation.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side

и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending order DES-
	CEND 21: in descending order If mark != NULL: in the user-defined order
mark	Pointer to NULL or to the user-defined ordering
weight	Over-relaxation weight

Author

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 08/03/2012

Definition at line 870 of file smoother_bsr.c.

9.86.2.12 void fasp_smoother_dbsr_sor1 (dBSRmat * A, dvector * b, dvector * u, INT order, INT * mark, REAL * diaginv, REAL weight)

SOR relaxation.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending order DES-
	CEND 21: in descending order If mark != NULL: in the user-defined order
mark	Pointer to NULL or to the user-defined ordering
diaginv	Inverses for all the diagonal blocks of A
weight	Over-relaxation weight

Author

Zhiyang Zhou

Date

2010/10/25

Definition at line 992 of file smoother_bsr.c.

9.86.2.13 void fasp_smoother_dbsr_sor_ascend (dBSRmat * A, dvector * b, dvector * u, REAL * diaginv, REAL weight)

SOR relaxation in the ascending order.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
diaginv	Inverses for all the diagonal blocks of A
weight	Over-relaxation weight

Author

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 2012/09/04

Definition at line 1033 of file smoother_bsr.c.

9.86.2.14 void fasp_smoother_dbsr_sor_descend (dBSRmat * A, dvector * b, dvector * u, REAL * diaginv, REAL weight)

SOR relaxation in the descending order.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial guess, OUT: approximation)
diaginv	Inverses for all the diagonal blocks of A
weight	Over-relaxation weight

Author

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 2012/09/04

Definition at line 1162 of file smoother_bsr.c.

9.86.2.15 void fasp_smoother_dbsr_sor_order (dBSRmat * A, dvector * b, dvector * u, REAL * diaginv, INT * mark, REAL weight)

SOR relaxation in the user-defined order.

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
diaginv	Inverses for all the diagonal blocks of A
mark	Pointer to the user-defined ordering
weight	Over-relaxation weight

Author

Zhiyang Zhou

Date

2010/10/25

Modified by Chunsheng Feng, Zheng Li on 2012/09/04

Definition at line 1293 of file smoother_bsr.c.

9.87 smoother csr.c File Reference

Smoothers for dCSRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void fasp_smoother_dcsr_jacobi (dvector *u, const INT i_1, const INT i_n, const INT s, dCSRmat *A, dvector *b, INT L)

Jacobi method as a smoother.

void fasp_smoother_dcsr_gs (dvector *u, const INT i_1, const INT i_n, const INT s, dCSRmat *A, dvector *b, INT L)

Gauss-Seidel method as a smoother.

- void fasp_smoother_dcsr_gs_cf (dvector *u, dCSRmat *A, dvector *b, INT L, INT *mark, const INT order)

 Gauss-Seidel smoother with C/F ordering for Au=b.
- void fasp_smoother_dcsr_sgs (dvector *u, dCSRmat *A, dvector *b, INT L)

Symmetric Gauss-Seidel method as a smoother.

void fasp_smoother_dcsr_sor (dvector *u, const INT i_1, const INT i_n, const INT s, dCSRmat *A, dvector *b, INT L, const REAL w)

SOR method as a smoother.

void fasp_smoother_dcsr_sor_cf (dvector *u, dCSRmat *A, dvector *b, INT L, const REAL w, INT *mark, const INT order)

SOR smoother with C/F ordering for Au=b.

void fasp_smoother_dcsr_ilu (dCSRmat *A, dvector *b, dvector *x, void *data)

ILU method as a smoother.

void fasp_smoother_dcsr_kaczmarz (dvector *u, const INT i_1, const INT i_n, const INT s, dCSRmat *A, dvector *b, INT L, const REAL w)

Kaczmarz method as a smoother.

void fasp_smoother_dcsr_L1diag (dvector *u, const INT i_1, const INT i_n, const INT s, dCSRmat *A, dvector *b, INT L)

Diagonal scaling (using L1 norm) as a smoother.

void fasp_smoother_dcsr_gs_rb3d (dvector *u, dCSRmat *A, dvector *b, INT L, INT order, INT *mark, INT maximap, INT nx, INT ny, INT nz)

9.87.1 Detailed Description

Smoothers for dCSRmat matrices.

Definition in file smoother_csr.c.

9.87.2 Function Documentation

9.87.2.1 void fasp_smoother_dcsr_gs (dvector * u, const INT i_1, const INT i_n, const INT s, dCSRmat * A, dvector * b, INT L)

Gauss-Seidel method as a smoother.

Parameters

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
<u>i_1</u>	Starting index
i_n	Ending index
s	Increasing step
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations

Author

Xuehai Huang, Chensong Zhang

Date

09/26/2009

Modified by Chunsheng Feng, Zheng Li on 09/01/2012

Definition at line 195 of file smoother_csr.c.

9.87.2.2 void fasp_smoother_dcsr_gs_cf (dvector * u, dCSRmat * A, dvector * b, INT L, INT * mark, const INT order)

Gauss-Seidel smoother with C/F ordering for Au=b.

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations
mark	C/F marker array
order	C/F ordering: -1: F-first; 1: C-first

Author

Zhiyang Zhou

Date

11/12/2010

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/24/2012

Definition at line 364 of file smoother_csr.c.

9.87.2.3 void fasp_smoother_dcsr_ilu (dCSRmat * A, dvector * b, dvector * x, void * data)

ILU method as a smoother.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
Χ	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
data	Pointer to user defined data

Author

Shiquan Zhang, Xiaozhe Hu

Date

2010/11/12

form residual zr = b - Ax

Definition at line 1067 of file smoother_csr.c.

9.87.2.4 void fasp_smoother_dcsr_jacobi (dvector * u, const INT i_1, const INT i_n, const INT s, dCSRmat * A, dvector * b, INT L)

Jacobi method as a smoother.

Parameters

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
<u>i_1</u>	Starting index
<u>i_</u> n	Ending index
s	Increasing step
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations

Author

Xuehai Huang, Chensong Zhang

Date

09/26/2009

Modified by Chunsheng Feng, Zheng Li on 08/29/2012

Definition at line 59 of file smoother_csr.c.

9.87.2.5 void fasp_smoother_dcsr_kaczmarz (dvector *u, const INT i_1, const INT i_n, const INT s, dCSRmat *A, dvector *b, INT L, const REAL w)

Kaczmarz method as a smoother.

Parameters

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
<u>i_1</u>	Starting index
i_n	Ending index
s	Increasing step
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations
W	Over-relaxation weight

Author

Xiaozhe Hu

Date

2010/11/12

Modified by Chunsheng Feng, Zheng Li on 2012/09/01

Definition at line 1144 of file smoother_csr.c.

9.87.2.6 void fasp_smoother_dcsr_L1diag (dvector *u, const INT i_1, const INT i_n, const INT s, dCSRmat *A, dvector *b, INT L)

Diagonal scaling (using L1 norm) as a smoother.

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
<u>i_</u> 1	Starting index
<u>i_</u> n	Ending index
S	Increasing step
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations

Author

Xiaozhe Hu, James Brannick

Date

01/26/2011

Modified by Chunsheng Feng, Zheng Li on 09/01/2012

Definition at line 1285 of file smoother_csr.c.

9.87.2.7 void fasp_smoother_dcsr_sgs (dvector * u, dCSRmat * A, dvector * b, INT L)

Symmetric Gauss-Seidel method as a smoother.

Parameters

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations

Author

Xiaozhe Hu

Date

10/26/2010

Modified by Chunsheng Feng, Zheng Li on 09/01/2012

Definition at line 629 of file smoother_csr.c.

9.87.2.8 void fasp_smoother_dcsr_sor (dvector *u, const INT i_1, const INT i_n, const INT s, dCSRmat *A, dvector *b, INT L, const REAL w)

SOR method as a smoother.

Parameters

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
<u>i_1</u>	Starting index
i_n	Ending index
s	Increasing step
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations
W	Over-relaxation weight

Author

Xiaozhe Hu

Date

10/26/2010

Modified by Chunsheng Feng, Zheng Li on 09/01/2012

Definition at line 745 of file smoother_csr.c.

9.87.2.9 void fasp_smoother_dcsr_sor_cf (dvector * u, dCSRmat * A, dvector * b, INT L, const REAL w, INT * mark, const INT order)

SOR smoother with C/F ordering for Au=b.

Parameters

и	Pointer to dvector: the unknowns (IN: initial, OUT: approximation)
Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
L	Number of iterations
W	Over-relaxation weight
mark	C/F marker array
order	C/F ordering: -1: F-first; 1: C-first

Author

Zhiyang Zhou

Date

2010/11/12

Modified by Chunsheng Feng, Zheng Li on 08/29/2012

Definition at line 873 of file smoother_csr.c.

9.88 smoother_csr_cr.c File Reference

Smoothers for dCSRmat matrices using compatible relaxation.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void fasp_smoother_dcsr_gscr (INT pt, INT n, REAL *u, INT *ia, INT *ja, REAL *a, REAL *b, INT L, INT *CF)
 Gauss Seidel method restriced to a block.

9.88.1 Detailed Description

Smoothers for dCSRmat matrices using compatible relaxation.

Note

Restricted-smoothers for compatible relaxation, C/F smoothing, etc.

Definition in file smoother_csr_cr.c.

9.88.2 Function Documentation

9.88.2.1 void fasp_smoother_dcsr_gscr (INT pt, INT n, REAL * u, INT * ia, INT * ja, REAL * a, REAL * b, INT L, INT * CF)

Gauss Seidel method restriced to a block.

Parameters

pt	Relax type, e.g., cpt, fpt, etc
n	Number of variables
и	Iterated solution
ia	Row pointer
ja	Column index
а	Pointers to sparse matrix values in CSR format
b	Pointer to right hand side – remove later also as MG relaxation on error eqn
L	Number of iterations
CF	Marker for C, F points

Author

James Brannick

Date

09/07/2010

Note

Gauss Seidel CR smoother (Smoother_Type = 99)

Definition at line 38 of file smoother_csr_cr.c.

9.89 smoother_csr_poly.c File Reference

Smoothers for dCSRmat matrices using poly. approx. to A^{-1} .

```
#include <math.h>
#include <time.h>
#include <float.h>
#include <limits.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

- void fasp_smoother_dcsr_poly (dCSRmat *Amat, dvector *brhs, dvector *usol, INT n, INT ndeg, INT L)
 poly approx to A^{-1} as MG smoother
- void fasp_smoother_dcsr_poly_old (dCSRmat *Amat, dvector *brhs, dvector *usol, INT n, INT ndeg, INT L)
 poly approx to A^{-1} as MG smoother: JK<Z2010

9.89.1 Detailed Description

Smoothers for dCSRmat matrices using poly. approx. to A^{\land} {-1}.

Definition in file smoother_csr_poly.c.

9.89.2 Function Documentation

9.89.2.1 void fasp_smoother_dcsr_poly (dCSRmat * Amat, dvector * brhs, dvector * usol, INT n, INT ndeg, INT L)

poly approx to $A^{\setminus}\{-1\}$ as MG smoother

Parameters

Amat	Pointer to stiffness matrix, consider square matrix.
brhs	Pointer to right hand side
usol	Pointer to solution
n	Problem size
ndeg	Degree of poly
L	Number of iterations

Author

Fei Cao, Xiaozhe Hu

Date

05/24/2012

Definition at line 46 of file smoother csr poly.c.

9.89.2.2 void fasp_smoother_dcsr_poly_old (dCSRmat * Amat, dvector * brhs, dvector * usol, INT n, INT ndeg, INT L)

poly approx to A^{-1} as MG smoother: JK<Z2010

Amat	Pointer to stiffness matrix
brhs	Pointer to right hand side
usol	Pointer to solution
n	Problem size
ndeg	Degree of poly
L	Number of iterations

Author

James Brannick and Ludmil T Zikatanov

Date

06/28/2010

Modified by Chunsheng Feng, Zheng Li on 10/18/2012

Definition at line 141 of file smoother_csr_poly.c.

9.90 smoother str.c File Reference

Smoothers for dSTRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

• void fasp_smoother_dstr_jacobi (dSTRmat *A, dvector *b, dvector *u)

Jacobi method as the smoother.

Gauss-Seidel method as the smoother in the ascending manner.

- void fasp_smoother_dstr_jacobi1 (dSTRmat *A, dvector *b, dvector *u, REAL *diaginv)

 Jacobi method as the smoother with diag_inv given.
- void fasp_smoother_dstr_gs (dSTRmat *A, dvector *b, dvector *u, INT order, INT *mark)
 Gauss-Seidel method as the smoother.
- void fasp_smoother_dstr_gs1 (dSTRmat *A, dvector *b, dvector *u, INT order, INT *mark, REAL *diaginv)

 Gauss-Seidel method as the smoother with diag_inv given.
- void fasp_smoother_dstr_gs_ascend (dSTRmat *A, dvector *b, dvector *u, REAL *diaginv)
- void fasp_smoother_dstr_gs_descend (dSTRmat *A, dvector *b, dvector *u, REAL *diaginv)
- Gauss-Seidel method as the smoother in the descending manner.

 void fasp_smoother_dstr_gs_order (dSTRmat *A, dvector *b, dvector *u, REAL *diaginv, INT *mark)
- Gauss method as the smoother in the user-defined order.
- void fasp_smoother_dstr_gs_cf (dSTRmat *A, dvector *b, dvector *u, REAL *diaginv, INT *mark, INT order)
 Gauss method as the smoother in the C-F manner.
- void fasp_smoother_dstr_sor (dSTRmat *A, dvector *b, dvector *u, INT order, INT *mark, REAL weight) SOR method as the smoother.

void fasp_smoother_dstr_sor1 (dSTRmat *A, dvector *b, dvector *u, INT order, INT *mark, REAL *diaginv, REAL weight)

SOR method as the smoother.

- void fasp_smoother_dstr_sor_ascend (dSTRmat *A, dvector *b, dvector *u, REAL *diaginv, REAL weight) SOR method as the smoother in the ascending manner.
- void fasp_smoother_dstr_sor_descend (dSTRmat *A, dvector *b, dvector *u, REAL *diaginv, REAL weight)
 SOR method as the smoother in the descending manner.
- void fasp_smoother_dstr_sor_order (dSTRmat *A, dvector *b, dvector *u, REAL *diaginv, INT *mark, REAL weight)

SOR method as the smoother in the user-defined order.

 void fasp_smoother_dstr_sor_cf (dSTRmat *A, dvector *b, dvector *u, REAL *diaginv, INT *mark, INT order, REAL weight)

SOR method as the smoother in the C-F manner.

- $\bullet \ \ void \ fasp_generate_diaginv_block \ (dSTRmat *A, ivector *neigh, dvector *diaginv, ivector *pivot)\\$
- Generate inverse of diagonal block for block smoothers.

 void fasp_smoother_dstr_schwarz (dSTRmat *A, dvector *b, dvector *u, dvector *diaginv, ivector *pivot, ivector

Schwarz method as the smoother.

9.90.1 Detailed Description

Smoothers for dSTRmat matrices.

*neigh, ivector *order)

Definition in file smoother str.c.

9.90.2 Function Documentation

9.90.2.1 void fasp_generate_diaginv_block (dSTRmat * A, ivector * neigh, dvector * diaginv, ivector * pivot)

Generate inverse of diagonal block for block smoothers.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
neigh	Pointer to ivector: neighborhoods
diaginv	Pointer to dvector: the inverse of the diagonals
pivot	Pointer to ivector: the pivot of diagonal blocks

Author

Xiaozhe Hu

Date

10/01/2011

Definition at line 1517 of file smoother_str.c.

9.90.2.2 void fasp_smoother_dstr_gs (dSTRmat * A, dvector * b, dvector * u, INT order, INT * mark)

Gauss-Seidel method as the smoother.

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending manner D-ESCEND 21: in descending manner If mark != NULL USERDEFINED 0: in the user-defined manner CPFIRST 1: C-points first and then F-points FPFIRST -1: F-points first and then C-points
mark	Pointer to the user-defined ordering(when order=0) or CF_marker array(when order!=0)

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 202 of file smoother_str.c.

9.90.2.3 void fasp_smoother_dstr_gs1 (dSTRmat * A, dvector * b, dvector * u, INT order, INT * mark, REAL * diaginv)

Gauss-Seidel method as the smoother with diag_inv given.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending manner D-
	ESCEND 21: in descending manner If mark != NULL USERDEFINED 0 : in the user-defined
	manner CPFIRST 1: C-points first and then F-points FPFIRST -1: F-points first and then C-
	points
mark	Pointer to the user-defined ordering(when order=0) or CF_marker array(when order!=0)
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 261 of file smoother_str.c.

9.90.2.4 void fasp_smoother_dstr_gs_ascend (dSTRmat*A, dvector*b, dvector*u, REAL*diaginv)

Gauss-Seidel method as the smoother in the ascending manner.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 306 of file smoother_str.c.

9.90.2.5 void fasp_smoother_dstr_gs_cf (dSTRmat * A, dvector * b, dvector * u, REAL * diaginv, INT * mark, INT order)

Gauss method as the smoother in the C-F manner.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1
mark	Pointer to the user-defined order array
order	Flag to indicate the order for smoothing CPFIRST 1 : C-points first and then F-points FPFIRST
	-1 : F-points first and then C-points

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 660 of file smoother_str.c.

9.90.2.6 void fasp_smoother_dstr_gs_descend (dSTRmat * A, dvector * b, dvector * u, REAL * diaginv)

Gauss-Seidel method as the smoother in the descending manner.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 421 of file smoother_str.c.

9.90.2.7 void fasp_smoother_dstr_gs_order (dSTRmat * A, dvector * b, dvector * u, REAL * diaginv, INT * mark)

Gauss method as the smoother in the user-defined order.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1
mark	Pointer to the user-defined order array

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 538 of file smoother_str.c.

9.90.2.8 void fasp_smoother_dstr_jacobi (dSTRmat * A, dvector * b, dvector * u)

Jacobi method as the smoother.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 31 of file smoother_str.c.

9.90.2.9 void fasp_smoother_dstr_jacobi1 (dSTRmat * A, dvector * b, dvector * u, REAL * diaginv)

Jacobi method as the smoother with diag_inv given.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 79 of file smoother_str.c.

9.90.2.10 void fasp_smoother_dstr_schwarz (dSTRmat * A, dvector * b, dvector * u, dvector * diaginv, ivector * pivot, ivector * neigh, ivector * order)

Schwarz method as the smoother.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	Pointer to dvector: the inverse of the diagonals
pivot	Pointer to ivector: the pivot of diagonal blocks
neigh	Pointer to ivector: neighborhoods
order	Pointer to ivector: the smoothing order

Author

Xiaozhe Hu

Date

10/01/2011

Definition at line 1639 of file smoother_str.c.

9.90.2.11 void fasp_smoother_dstr_sor (dSTRmat * A, dvector * b, dvector * u, INT order, INT * mark, REAL weight)

SOR method as the smoother.

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending manner D-ESCEND 21: in descending manner If mark != NULL USERDEFINED 0: in the user-defined manner CPFIRST 1: C-points first and then F-points FPFIRST -1: F-points first and then C-points
mark	Pointer to the user-defined ordering(when order=0) or CF_marker array(when order!=0)
weight	Over-relaxation weight

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 851 of file smoother_str.c.

9.90.2.12 void fasp_smoother_dstr_sor1 (dSTRmat * A, dvector * b, dvector * u, INT order, INT * mark, REAL * diaginv, REAL weight)

SOR method as the smoother.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
order	Flag to indicate the order for smoothing If mark = NULL ASCEND 12: in ascending manner D-ESCEND 21: in descending manner If mark != NULL USERDEFINED 0: in the user-defined manner CPFIRST 1: C-points first and then F-points FPFIRST -1: F-points first and then C-points
mark	Pointer to the user-defined ordering(when order=0) or CF_marker array(when order!=0)
diaginv	Inverse of the diagonal entries
weight	Over-relaxation weight

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 912 of file smoother_str.c.

9.90.2.13 void fasp_smoother_dstr_sor_ascend (dSTRmat * A, dvector * b, dvector * u, REAL * diaginv, REAL weight)

SOR method as the smoother in the ascending manner.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1
weight	Over-relaxation weight

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 958 of file smoother_str.c.

9.90.2.14 void fasp_smoother_dstr_sor_cf (dSTRmat * A, dvector * b, dvector * u, REAL * diaginv, INT * mark, INT order, REAL weight)

SOR method as the smoother in the C-F manner.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1
mark	Pointer to the user-defined order array
order	Flag to indicate the order for smoothing CPFIRST 1 : C-points first and then F-points FPFIRST
	-1: F-points first and then C-points
weight	Over-relaxation weight

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 1330 of file smoother_str.c.

9.90.2.15 void fasp_smoother_dstr_sor_descend (dSTRmat * A, dvector * b, dvector * u, REAL * diaginv, REAL weight)

SOR method as the smoother in the descending manner.

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1
weight	Over-relaxation weight

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 1078 of file smoother_str.c.

9.90.2.16 void fasp_smoother_dstr_sor_order (dSTRmat * A, dvector * b, dvector * u, REAL * diaginv, INT * mark, REAL weight)

SOR method as the smoother in the user-defined order.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
diaginv	All the inverse matrices for all the diagonal block of A when (A->nc)>1, and NULL when (A-
	>nc)=1
mark	Pointer to the user-defined order array
weight	Over-relaxation weight

Author

Shiquan Zhang, Zhiyang Zhou

Date

10/10/2010

Definition at line 1199 of file smoother_str.c.

9.91 sparse_block.c File Reference

Sparse matrix block operations.

```
#include <time.h>
#include "fasp.h"
#include "fasp_block.h"
#include "fasp_functs.h"
```

Functions

SHORT fasp_dcsr_getblk (dCSRmat *A, INT *Is, INT *Js, INT m, INT n, dCSRmat *B)
 Get a sub CSR matrix of A with specified rows and colums.

• SHORT fasp_dbsr_getblk (dBSRmat *A, INT *Is, INT *Js, INT m, INT n, dBSRmat *B)

Get a sub BSR matrix of A with specified rows and columns.

dCSRmat fasp_dbsr_getblk_dcsr (dBSRmat *A)

get dCSRmat block from a dBSRmat matrix

9.91.1 Detailed Description

Sparse matrix block operations.

Definition in file sparse block.c.

9.91.2 Function Documentation

9.91.2.1 SHORT fasp_dbsr_getblk (dBSRmat * A, INT * Is, INT * Js, INT m, INT n, dBSRmat * B)

Get a sub BSR matrix of A with specified rows and columns.

Parameters

Α	Pointer to dBSRmat BSR matrix
В	Pointer to dBSRmat BSR matrix
Is	Pointer to selected rows
Js	Pointer to selected colums
m	Number of selected rows
n	Number of selected colums

Returns

SUCCESS if successed, otherwise return error information.

Author

Shiquan Zhang, Xiaozhe Hu

Date

12/25/2010

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 132 of file sparse_block.c.

9.91.2.2 dCSRmat fasp_dbsr_getblk_dcsr (dBSRmat * A)

get dCSRmat block from a dBSRmat matrix

*A	Pointer to the BSR format matrix

Returns

dCSRmat matrix if succeed, NULL if fail

Author

Xiaozhe Hu

Date

03/16/2012

Definition at line 226 of file sparse_block.c.

```
9.91.2.3 SHORT fasp_dcsr_getblk ( dCSRmat * A, INT * Is, INT * Js, INT m, INT n, dCSRmat * B )
```

Get a sub CSR matrix of A with specified rows and colums.

Parameters

Α	Pointer to dCSRmat matrix
В	Pointer to dCSRmat matrix
Is	Pointer to selected rows
Js	Pointer to selected colums
m	Number of selected rows
n	Number of selected colums

Returns

SUCCESS if successed, otherwise return error information.

Author

Shiquan Zhang, Xiaozhe Hu

Date

12/25/2010

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 39 of file sparse_block.c.

9.92 sparse_bsr.c File Reference

Sparse matrix operations for dBSRmat matrices.

```
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

dBSRmat fasp dbsr create (INT ROW, INT COL, INT NNZ, INT nb, INT storage manner)

Create BSR sparse matrix data memory space.

void fasp dbsr alloc (INT ROW, INT COL, INT NNZ, INT nb, INT storage manner, dBSRmat *A)

Allocate memory space for BSR format sparse matrix.

void fasp_dbsr_free (dBSRmat *A)

Free memeory space for BSR format sparse matrix.

void fasp dbsr null (dBSRmat *A)

Initialize sparse matrix on structured grid.

void fasp_dbsr_cp (dBSRmat *A, dBSRmat *B)

copy a dCSRmat to a new one B=A

INT fasp dbsr trans (dBSRmat *A, dBSRmat *AT)

Find $A^{\wedge}T$ from given dBSRmat matrix A.

SHORT fasp_dbsr_diagpref (dBSRmat *A)

Reorder the column and data arrays of a square BSR matrix, so that the first entry in each row is the diagonal one.

dvector fasp_dbsr_getdiaginv (dBSRmat *A)

Get D^{\wedge} {-1} of matrix A.

dBSRmat fasp_dbsr_diaginv (dBSRmat *A)

Compute $B := D^{\setminus} \{-1\} * A$, where 'D' is the block diagonal part of A.

dBSRmat fasp_dbsr_diaginv2 (dBSRmat *A, REAL *diaginv)

Compute $B := D^{\setminus} \{-1\} * A$, where 'D' is the block diagonal part of A.

dBSRmat fasp_dbsr_diaginv3 (dBSRmat *A, REAL *diaginv)

Compute $B := D^{\wedge} \{-1\} * A$, where 'D' is the block diagonal part of A.

dBSRmat fasp_dbsr_diaginv4 (dBSRmat *A, REAL *diaginv)

Compute $B := D^{\setminus} \{-1\} * A$, where 'D' is the block diagonal part of A.

void fasp_dbsr_getdiag (INT n, dBSRmat *A, REAL *diag)

Abstract the diagonal blocks of a BSR matrix.

9.92.1 Detailed Description

Sparse matrix operations for dBSRmat matrices.

Definition in file sparse_bsr.c.

9.92.2 Function Documentation

9.92.2.1 void fasp_dbsr_alloc (INT ROW, INT COL, INT NNZ, INT nb, INT storage_manner, dBSRmat * A)

Allocate memory space for BSR format sparse matrix.

Parameters

ROW	Number of rows of block
COL	Number of columns of block

NNZ	Number of nonzero blocks
nb	Dimension of exch block
storage_manner	Storage manner for each sub-block
Α	Pointer to new dBSRmat matrix

Author

Xiaozhe Hu

Date

10/26/2010

Definition at line 84 of file sparse_bsr.c.

9.92.2.2 void fasp_dbsr_cp (dBSRmat * A, dBSRmat * B)

copy a dCSRmat to a new one B=A

Parameters

Α	Pointer to the dBSRmat matrix
В	Pointer to the dBSRmat matrix

Author

Xiaozhe Hu

Date

08/07/2011

Definition at line 178 of file sparse_bsr.c.

9.92.2.3 dBSRmat fasp_dbsr_create (INT ROW, INT COL, INT NNZ, INT nb, INT storage_manner)

Create BSR sparse matrix data memory space.

Parameters

ROW	Number of rows of block
COL	Number of columns of block
NNZ	Number of nonzero blocks
nb	Dimension of exch block
storage_manner	Storage manner for each sub-block

Returns

A The new dBSRmat matrix

Author

Xiaozhe Hu

Date

10/26/2010

Definition at line 33 of file sparse_bsr.c.

9.92.2.4 dBSRmat fasp_dbsr_diaginv (dBSRmat * A)

Compute B := $D^{-1}*A$, where 'D' is the block diagonal part of A.

Parameters

A Pointer to the dBSRmat matrix

Author

Zhiyang Zhou

Date

2010/10/26

Note

Works for general nb (Xiaozhe)

Modified by Chunsheng Feng, Zheng Li on 08/25/2012

Definition at line 502 of file sparse_bsr.c.

9.92.2.5 dBSRmat fasp_dbsr_diaginv2 (dBSRmat * A, REAL * diaginv)

Compute B := $D^{\{-1\}}*A$, where 'D' is the block diagonal part of A.

Parameters

-	Pointer to the dBSRmat matrix
diagin	Pointer to the inverses of all the diagonal blocks

Author

Zhiyang Zhou

Date

2010/11/07

Note

Works for general nb (Xiaozhe)

Modified by Chunsheng Feng, Zheng Li on 08/25/2012

Definition at line 664 of file sparse_bsr.c.

9.92.2.6 dBSRmat fasp_dbsr_diaginv3 (dBSRmat * A, REAL * diaginv)

Compute B := $D^{-1}*A$, where 'D' is the block diagonal part of A.

Α	Pointer to the dBSRmat matrix
diaginv	Pointer to the inverses of all the diagonal blocks

Returns

BSR matrix after diagonal scaling

Author

Xiaozhe Hu

Date

12/25/2010

Note

Works for general nb (Xiaozhe)

Modified by Xiaozhe Hu on 05/26/2012

Definition at line 766 of file sparse_bsr.c.

9.92.2.7 dBSRmat fasp_dbsr_diaginv4 (dBSRmat * A, REAL * diaginv)

Compute B := $D^{-1}*A$, where 'D' is the block diagonal part of A.

Parameters

Α	Pointer to the dBSRmat matrix
diaginv	Pointer to the inverses of all the diagonal blocks

Returns

BSR matrix after diagonal scaling

Note

Works for general nb (Xiaozhe)

A is preordered that the first block of each row is the diagonal block!

Author

Xiaozhe Hu

Date

03/12/2011

Modified by Chunsheng Feng, Zheng Li on 08/26/2012

Definition at line 1124 of file sparse_bsr.c.

9.92.2.8 SHORT fasp_dbsr_diagpref (dBSRmat * A)

Reorder the column and data arrays of a square BSR matrix, so that the first entry in each row is the diagonal one.

Parameters

A Pointer to the BSR matrix

Author

Xiaozhe Hu

Date

03/10/2011

Author

Chunsheng Feng, Zheng Li

Date

09/02/2012

Note

Reordering is done in place.

Definition at line 289 of file sparse_bsr.c.

9.92.2.9 void fasp_dbsr_free (dBSRmat * A)

Free memeory space for BSR format sparse matrix.

Parameters

A Pointer to the dBSRmat matrix

Author

Xiaozhe Hu

Date

10/26/2010

Definition at line 130 of file sparse_bsr.c.

9.92.2.10 fasp_dbsr_getdiag (INT n, dBSRmat * A, REAL * diag)

Abstract the diagonal blocks of a BSR matrix.

Parameters

n	Number of blocks to get
Α	Pointer to the 'dBSRmat' type matrix
diag	Pointer to array which stores the diagonal blocks in row by row manner

Author

Zhiyang Zhou

Date

2010/10/26

Note

Works for general nb (Xiaozhe)

Modified by Chunsheng Feng, Zheng Li on 08/25/2012

Definition at line 1417 of file sparse_bsr.c.

9.92.2.11 dvector fasp_dbsr_getdiaginv (dBSRmat * A)

Get $D^{\setminus}\{-1\}$ of matrix A.

Parameters

A Pointer to the dBSRmat matrix

Author

Xiaozhe Hu

Date

02/19/2013

Note

Works for general nb (Xiaozhe)

Definition at line 398 of file sparse_bsr.c.

9.92.2.12 void fasp_dbsr_null (dBSRmat * A)

Initialize sparse matrix on structured grid.

Parameters

A Pointer to the dBSRmat matrix

Author

Xiaozhe Hu

Date

10/26/2010

Definition at line 155 of file sparse_bsr.c.

```
9.92.2.13 INT fasp_dbsr_trans ( dBSRmat * A, dBSRmat * AT )
```

Find A^{\(\Delta\)}T from given dBSRmat matrix A.

Parameters

Α	Pointer to the dBSRmat matrix
AT	Pointer to the transpose of dBSRmat matrix A

Author

Chunsheng FENG

Date

2011/06/08

Modified by Xiaozhe Hu (08/06/2011)

Definition at line 205 of file sparse_bsr.c.

9.93 sparse_coo.c File Reference

Sparse matrix operations for dCOOmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

dCOOmat fasp_dcoo_create (INT m, INT n, INT nnz)

Create IJ sparse matrix data memory space.

void fasp_dcoo_alloc (const INT m, const INT n, const INT nnz, dCOOmat *A)

Allocate COO sparse matrix memory space.

void fasp_dcoo_free (dCOOmat *A)

Free IJ sparse matrix data memeory space.

void fasp_dcoo_shift (dCOOmat *A, INT offset)

Reindex a REAL matrix in IJ format to make the index starting from 0 or 1.

9.93.1 Detailed Description

Sparse matrix operations for dCOOmat matrices.

Definition in file sparse_coo.c.

9.93.2 Function Documentation

9.93.2.1 void fasp_dcoo_alloc (const INT m, const INT n, const INT nnz, dCOOmat * A)

Allocate COO sparse matrix memory space.

Parameters

m	Number of rows
n	Number of columns
nnz	Number of nonzeros
Α	Pointer to the dCSRmat matrix

Author

Xiaozhe Hu

Date

03/25/2013

Definition at line 62 of file sparse_coo.c.

9.93.2.2 dCOOmat fasp_dcoo_create (INT m, INT n, INT nnz)

Create IJ sparse matrix data memory space.

Parameters

m	Number of rows
n	Number of columns
nnz	Number of nonzeros

Returns

A The new dCOOmat matrix

Author

Chensong Zhang

Date

2010/04/06

Definition at line 34 of file sparse_coo.c.

9.93.2.3 void fasp_dcoo_free (dCOOmat * A)

Free IJ sparse matrix data memeory space.

Parameters

A	Pointer to the dCOOmat matrix

Author

Chensong Zhang

Date

2010/04/03

Definition at line 95 of file sparse_coo.c.

```
9.93.2.4 void fasp_dcoo_shift ( dCOOmat * A, INT offset )
```

Reindex a REAL matrix in IJ format to make the index starting from 0 or 1.

Parameters

Α	Pointer to IJ matrix
offset	Size of offset (1 or -1)

Author

Chensong Zhang

Date

2010/04/06

Modified by Chunsheng Feng, Zheng Li on 08/25/2012

Definition at line 117 of file sparse_coo.c.

9.94 sparse_csr.c File Reference

Sparse matrix operations for dCSRmat matrices.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

dCSRmat fasp_dcsr_create (const INT m, const INT n, const INT nnz)

Create CSR sparse matrix data memory space.

iCSRmat fasp_icsr_create (const INT m, const INT n, const INT nnz)

Create CSR sparse matrix data memory space.

void fasp dcsr alloc (const INT m, const INT n, const INT nnz, dCSRmat *A)

Allocate CSR sparse matrix memory space.

void fasp_dcsr_free (dCSRmat *A)

Free CSR sparse matrix data memeory space.

void fasp icsr free (iCSRmat *A)

Free CSR sparse matrix data memeory space.

void fasp_dcsr_null (dCSRmat *A)

Initialize CSR sparse matrix.

void fasp_icsr_null (iCSRmat *A)

Initialize CSR sparse matrix.

dCSRmat fasp dcsr perm (dCSRmat *A, INT *P)

Apply permutation of A, i.e. Aperm=PAP' by the orders given in P.

void fasp dcsr sort (dCSRmat *A)

Sort each row of A in ascending order w.r.t. column indices.

void fasp_dcsr_getdiag (INT n, dCSRmat *A, dvector *diag)

Get first n diagonal entries of a CSR matrix A.

void fasp dcsr getcol (const INT n, dCSRmat *A, REAL *col)

Get the n-th column of a CSR matrix A.

void fasp dcsr diagpref (dCSRmat *A)

Re-order the column and data arrays of a CSR matrix, so that the first entry in each row is the diagonal.

SHORT fasp_dcsr_regdiag (dCSRmat *A, REAL value)

Regularize diagonal entries of a CSR sparse matrix.

void fasp_icsr_cp (iCSRmat *A, iCSRmat *B)

Copy a iCSRmat to a new one B=A.

void fasp_dcsr_cp (dCSRmat *A, dCSRmat *B)

copy a dCSRmat to a new one B=A

void fasp icsr trans (iCSRmat *A, iCSRmat *AT)

Find transpose of iCSRmat matrix A.

INT fasp dcsr trans (dCSRmat *A, dCSRmat *AT)

Find tranpose of dCSRmat matrix A.

- void fasp_dcsr_transpose (INT *row[2], INT *col[2], REAL *val[2], INT *nn, INT *tniz)
- void fasp_dcsr_compress (dCSRmat *A, dCSRmat *B, REAL dtol)

Compress a CSR matrix A and store in CSR matrix B by dropping small entries abs(aij)<=dtol.

SHORT fasp_dcsr_compress_inplace (dCSRmat *A, REAL dtol)

Compress a CSR matrix A IN PLACE by dropping small entries abs(aij)<=dtol.

void fasp_dcsr_shift (dCSRmat *A, INT offset)

Reindex a REAL matrix in CSR format to make the index starting from 0 or 1.

void fasp_dcsr_symdiagscale (dCSRmat *A, dvector *diag)

Symmetric diagonal scaling D^{\wedge} {-1/2} AD^{\wedge} {-1/2}.

dCSRmat fasp_dcsr_sympat (dCSRmat *A)

Symmetrize the parttarn of a dCSRmat matrix.

void fasp_dcsr_multicoloring (dCSRmat *A, INT *flags, INT *groups)

Use the greedy multicoloring to get color groups of the adjacency graph of A.

9.94.1 Detailed Description

Sparse matrix operations for dCSRmat matrices.

Definition in file sparse csr.c.

9.94.2 Function Documentation

9.94.2.1 void fasp_dcsr_alloc (const INT m, const INT n, const INT nnz, dCSRmat * A)

Allocate CSR sparse matrix memory space.

Parameters

m	Number of rows
n	Number of columns
nnz	Number of nonzeros
Α	Pointer to the dCSRmat matrix

Author

Chensong Zhang

Date

2010/04/06

Definition at line 125 of file sparse_csr.c.

9.94.2.2 void fasp_dcsr_compress (dCSRmat * A, dCSRmat * B, REAL dtol)

Compress a CSR matrix A and store in CSR matrix B by dropping small entries abs(aij)<=dtol.

Parameters

Α	Pointer to dCSRmat CSR matrix
В	Pointer to dCSRmat CSR matrix
dtol	Drop tolerance

Author

Shiquan Zhang

Date

03/10/2010

Modified by Chunsheng Feng, Zheng Li on 08/25/2012

Definition at line 960 of file sparse_csr.c.

9.94.2.3 SHORT fasp_dcsr_compress_inplace (dCSRmat * A, REAL dtol)

Compress a CSR matrix A IN PLACE by dropping small entries abs(aij)<=dtol.

Parameters

Α	Pointer to dCSRmat CSR matrix
dtol	Drop tolerance

Author

Xiaozhe Hu

Date

12/25/2010

Modified by Chensong on 02/21/2013

Note

This routine can be modified for filtering.

Definition at line 1040 of file sparse_csr.c.

9.94.2.4 void fasp_dcsr_cp (dCSRmat * A, dCSRmat * B)

copy a dCSRmat to a new one B=A

Parameters

Α	Pointer to the dCSRmat matrix
В	Pointer to the dCSRmat matrix

Author

Chensong Zhang

Date

04/06/2010

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 722 of file sparse_csr.c.

9.94.2.5 dCSRmat fasp_dcsr_create (const INT m, const INT n, const INT nnz)

Create CSR sparse matrix data memory space.

Parameters

	т	Number of rows
Ī	n	Number of columns

nnz Number of nonzeros Returns A the new dCSRmat matrix **Author** Chensong Zhang Date 2010/04/06 Definition at line 34 of file sparse_csr.c. 9.94.2.6 void fasp_dcsr_diagpref (dCSRmat * A) Re-order the column and data arrays of a CSR matrix, so that the first entry in each row is the diagonal. **Parameters** Pointer to the matrix to be re-ordered Author Zhiyang Zhou Date 09/09/2010 Author Chunsheng Feng, Zheng Li Date 09/02/2012 Note Reordering is done in place. Modified by Chensong Zhang on Dec/21/2012 Definition at line 551 of file sparse_csr.c. 9.94.2.7 void fasp_dcsr_free (dCSRmat * A) Free CSR sparse matrix data memeory space.

Parameters

Α	Pointer to the dCSRmat matrix

Author

Chensong Zhang

Date

2010/04/06

Definition at line 166 of file sparse_csr.c.

9.94.2.8 void fasp_dcsr_getcol (const INT n, dCSRmat * A, REAL * col)

Get the n-th column of a CSR matrix A.

Parameters

n	Index of a column of A (0 \leq n \leq A.col-1)
Α	Pointer to dCSRmat CSR matrix
col	Pointer to the column

Author

Xiaozhe Hu

Date

11/07/2009

Modified by Chunsheng Feng, Zheng Li on 07/08/2012

Definition at line 472 of file sparse_csr.c.

9.94.2.9 void fasp_dcsr_getdiag (INT n, dCSRmat * A, dvector * diag)

Get first n diagonal entries of a CSR matrix A.

Parameters

n	Number of diag entries to get (if n=0, then get all diagonal entries)
Α	Pointer to dCSRmat CSR matrix
diag	Pointer to the diagonal as a dvector

Author

Chensong Zhang

Date

05/20/2009

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 408 of file sparse_csr.c.

9.94.2.10 void fasp_dcsr_multicoloring (dCSRmat * A, INT * flags, INT * groups)

Use the greedy multicoloring to get color groups of the adjacency graph of A.

Parameters

Α	Input dCSRmat
flags	flags for the independent group
groups	Return group numbers

Author

Chunsheng Feng

Date

09/15/2012

Definition at line 1272 of file sparse_csr.c.

9.94.2.11 void fasp_dcsr_null (dCSRmat * A)

Initialize CSR sparse matrix.

Parameters

Α	Pointer to the dCSRmat matrix

Author

Chensong Zhang

Date

2010/04/03

Definition at line 204 of file sparse_csr.c.

9.94.2.12 dCSRmat fasp_dcsr_perm (dCSRmat * A, INT * P)

Apply permutation of A, i.e. Aperm=PAP' by the orders given in P.

Parameters

Α	Pointer to the oringinal dCSRmat matrix
Р	Pointer to orders

Returns

The new ordered dCSRmat matrix if succeed, NULL if fail

Author

Shiquan Zhang

Date

03/10/2010

Note

P[i] = k means k-th row and column become i-th row and column!

Modified by Chunsheng Feng, Zheng Li on 07/12/2012

Definition at line 245 of file sparse_csr.c.

9.94.2.13 SHORT fasp_dcsr_regdiag (dCSRmat * A, REAL value)

Regularize diagonal entries of a CSR sparse matrix.

Parameters

ſ	Α	Pointer to the dCSRmat matrix
	value	Set a value on diag(A) which is too close to zero to "value"

Returns

SUCCESS if no diagonal entry is close to zero, else ERROR

Author

Shiquan Zhang

Date

11/07/2009

Definition at line 658 of file sparse_csr.c.

9.94.2.14 void fasp_dcsr_shift (dCSRmat * A, INT offset)

Reindex a REAL matrix in CSR format to make the index starting from 0 or 1.

Parameters

Α	Pointer to CSR matrix
offset	Size of offset (1 or -1)

Author

Chensong Zhang

Date

04/06/2010

Modified by chunsheng Feng, Zheng Li on 07/11/2012

Definition at line 1088 of file sparse_csr.c.

9.94.2.15 void fasp_dcsr_sort (dCSRmat * A)

Sort each row of A in ascending order w.r.t. column indices.

Parameters

Α	Pointer to the dCSRmat matrix
---	-------------------------------

Author

Shiquan Zhang

Date

06/10/2010

Definition at line 356 of file sparse_csr.c.

9.94.2.16 void fasp_dcsr_symdiagscale (dCSRmat * A, dvector * diag)

Symmetric diagonal scaling $D^{-1/2}AD^{-1/2}$.

Parameters

Α	Pointer to the dCSRmat matrix
diag	Pointer to the diagonal entries

Author

Xiaozhe Hu

Date

01/31/2011

Modified by Chunsheng Feng, Zheng Li on 07/11/2012

Definition at line 1151 of file sparse_csr.c.

9.94.2.17 dCSRmat fasp_dcsr_sympat (dCSRmat * A)

Symmetrize the parttarn of a dCSRmat matrix.

Parameters

*A	pointer to the dCSRmat matrix

Returns

symmetrized the dCSRmat matrix

Author

Xiaozhe Hu

Date

03/21/2011

Definition at line 1238 of file sparse_csr.c.

9.94.2.18 void fasp_dcsr_trans (dCSRmat * A, dCSRmat * AT)

Find tranpose of dCSRmat matrix A.

Parameters

Α	Pointer to the dCSRmat matrix
AT	Pointer to the transpose of dCSRmat matrix A (output)

Author

Chensong Zhang

Date

04/06/2010

Modified by Chunsheng Feng, Zheng Li on 06/20/2012

Definition at line 828 of file sparse_csr.c.

9.94.2.19 void fasp_icsr_cp (iCSRmat * A, iCSRmat * B)

Copy a iCSRmat to a new one B=A.

Parameters

Α	Pointer to the iCSRmat matrix
В	Pointer to the iCSRmat matrix

Author

Chensong Zhang

Date

05/16/2013

Definition at line 697 of file sparse_csr.c.

9.94.2.20 iCSRmat fasp_icsr_create (const INT m, const INT n, const INT nnz)

Create CSR sparse matrix data memory space.

Parameters

т	Number of rows
n	Number of columns
nnz	Number of nonzeros

Returns

A the new iCSRmat matrix

Author

Chensong Zhang

Date

2010/04/06

Definition at line 80 of file sparse_csr.c.

9.94.2.21 void fasp_icsr_free (iCSRmat * A)

Free CSR sparse matrix data memeory space.

Parameters

A Pointer to the iCSRmat matrix

Author

Chensong Zhang

Date

2010/04/06

Definition at line 185 of file sparse_csr.c.

9.94.2.22 void fasp_icsr_null (iCSRmat * A)

Initialize CSR sparse matrix.

Parameters

A Pointer to the iCSRmat matrix

Author

Chensong Zhang

Date

2010/04/03

Definition at line 221 of file sparse_csr.c.

9.94.2.23 void fasp_icsr_trans (iCSRmat * A, iCSRmat * AT)

Find transpose of iCSRmat matrix A.

Parameters

A Pointer to the iCSRmat matrix A

AT Pointer to the iCSRmat matrix A'

Returns

The transpose of iCSRmat matrix A

Author

Chensong Zhang

Date

04/06/2010

Modified by Chunsheng Feng, Zheng Li on 06/20/2012

Definition at line 749 of file sparse_csr.c.

9.95 sparse_csrl.c File Reference

Sparse matrix operations for dCSRLmat matrices.

```
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

dCSRLmat * fasp_dcsrl_create (INT num_rows, INT num_cols, INT num_nonzeros)

Create a dCSRLmat object.

void fasp_dcsrl_free (dCSRLmat *A)

Destroy a dCSRLmat object.

9.95.1 Detailed Description

Sparse matrix operations for dCSRLmat matrices.

Note

For details of CSRL format, refer to Optimizing sparse matrix vector product computations using unroll and jam by John Mellor-Crummey and John Garvin, Tech Report Rice Univ, Aug 2002.

Definition in file sparse_csrl.c.

9.95.2 Function Documentation

9.95.2.1 dCSRLmat * fasp_dcsrl_create (INT num_rows, INT num_cols, INT num_nonzeros)

Create a dCSRLmat object.

Parameters

num_rows	Number of rows
num_cols	Number of cols
num_nonzeros	Number of nonzero entries

Author

Zhiyang Zhou

Date

01/07/2001

Definition at line 30 of file sparse_csrl.c.

```
9.95.2.2 void fasp_dcsrl_free ( dCSRLmat * A )
```

Destroy a dCSRLmat object.

Parameters

Α	Pointer to the dCSRLmat type matrix
---	-------------------------------------

Author

Zhiyang Zhou

Date

01/07/2011

Definition at line 58 of file sparse_csrl.c.

9.96 sparse_str.c File Reference

Sparse matrix operations for dSTRmat matrices.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

void fasp_dstr_null (dSTRmat *A)

Initialize sparse matrix on structured grid.

dSTRmat fasp_dstr_create (INT nx, INT ny, INT nz, INT nc, INT nband, INT *offsets)

Create STR sparse matrix data memory space.

• void fasp_dstr_alloc (INT nx, INT ny, INT nz, INT nxy, INT ngrid, INT nband, INT nc, INT *offsets, dSTRmat *A)

Allocate STR sparse matrix memory space.

void fasp_dstr_free (dSTRmat *A)

Free STR sparse matrix data memeory space.

void fasp_dstr_cp (dSTRmat *A, dSTRmat *A1)

Copy a dSTRmat to a new one A1=A.

9.96.1 Detailed Description

Sparse matrix operations for dSTRmat matrices.

Definition in file sparse_str.c.

9.96.2 Function Documentation

9.96.2.1 void fasp_dstr_alloc (INT nx, INT ny, INT nz, INT nxy, INT ngrid, INT nband, INT nc, INT * offsets, dSTRmat * A)

Allocate STR sparse matrix memory space.

Parameters

nx	Number of grids in x direction
ny	Number of grids in y direction
nz	Number of grids in z direction
nxy	Number of grids in x-y plane
ngrid	Number of grids
nband	Number of off-diagonal bands
nc	Number of components
offsets	Shift from diagonal
Α	Pointer to the dSTRmat matrix

Author

Shiquan Zhang, Xiaozhe Hu

Date

05/17/2010

Definition at line 107 of file sparse_str.c.

9.96.2.2 void fasp_dstr_cp (dSTRmat * A, dSTRmat * A1)

Copy a dSTRmat to a new one A1=A.

Parameters

Α	Pointer to the dSTRmat matrix
A1	Pointer to the dSTRmat matrix

Author

Zhiyang Zhou

Date

04/21/2010

Definition at line 179 of file sparse_str.c.

9.96.2.3 dSTRmat fasp_dstr_create (INT nx, INT ny, INT nz, INT nc, INT nband, INT * offsets)

Create STR sparse matrix data memory space.

Parameters

nx	Number of grids in x direction
ny	Number of grids in y direction
nz	Number of grids in z direction
nc	Number of components
nband	Number of off-diagonal bands
offsets	Shift from diagonal

Returns

The dSTRmat matrix

Author

Shiquan Zhang, Xiaozhe Hu

Date

05/17/2010

Definition at line 56 of file sparse_str.c.

9.96.2.4 void fasp_dstr_free (dSTRmat * A)

Free STR sparse matrix data memeory space.

Parameters

A Pointer to the dSTRmat matrix

Author

Shiquan Zhang, Xiaozhe Hu

Date

05/17/2010

Definition at line 150 of file sparse_str.c.

9.96.2.5 void fasp_dstr_null (dSTRmat * A)

Initialize sparse matrix on structured grid.

Parameters

		_
Α	Pointer to the dSTRmat matrix	1

Author

Shiquan Zhang, Xiaozhe Hu

Date

05/17/2010

Definition at line 25 of file sparse str.c.

9.97 sparse_util.c File Reference

Routines for sparse matrix operations.

```
#include <math.h>
#include <time.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

- void fasp_sparse_abybms_ (INT *ia, INT *ja, INT *ib, INT *jb, INT *nap, INT *map, INT *mbp, INT *ic, INT *jc)
 Multiplication of two sparse matrices: calculating the nonzero structure of the result if jc is not null. If jc is null only finds num of nonzeroes.
- void fasp_sparse_abyb_ (INT *ia, INT *ja, REAL *a, INT *ib, INT *jb, REAL *b, INT *nap, INT *map, INT *mbp, INT *ic, INT *jc, REAL *c)

Multiplication of two sparse matrices: calculating the numerical values in the result.

- void fasp_sparse_iit_ (INT *ia, INT *ja, INT *na, INT *ma, INT *iat, INT *jat)
 - Transpose a boolean matrix (only given by ia, ja)
- void fasp_sparse_aat_ (INT *ia, INT *ja, REAL *a, INT *na, INT *ma, INT *iat, INT *jat, REAL *at)
 transpose a boolean matrix (only given by ia, ja)
- void fasp_sparse_aplbms_ (INT *ia, INT *ja, INT *ib, INT *jb, INT *nab, INT *mab, INT *ic, INT *jc)
 - Addition of two sparse matrices: calculating the nonzero structure of the result if jc is not null. if jc is null only finds num of nonzeroes.
- void fasp_sparse_aplusb_ (INT *ia, INT *ja, REAL *a, INT *ib, INT *jb, REAL *b, INT *nab, INT *mab, INT *ic, INT *jc, REAL *c)

Addition of two sparse matrices: calculating the numerical values in the result.

- void fasp_sparse_rapms_ (INT *ir, INT *jr, INT *ia, INT *ja, INT *jp, INT *jp, INT *nin, INT *ncin, INT *iac, INT *jac, INT *maxrout)
 - Calculates the nonzero structure of R*A*P, if jac is not null. If jac is null only finds num of nonzeroes.
- void fasp_sparse_wtams_ (INT *jw, INT *ia, INT *ja, INT *nwp, INT *map, INT *jv, INT *nvp, INT *icp)
 - Finds the nonzeroes in the result of $v^t = w^t A$, where w is a sparse vector and A is sparse matrix. jv is an integer array containing the indices of the nonzero elements in the result.
- void fasp_sparse_wta_ (INT *jw, REAL *w, INT *ia, INT *ja, REAL *a, INT *nwp, INT *map, INT *jv, REAL *v, INT *nvp)

Calculate $v^{\wedge}t = w^{\wedge}t$ A, where w is a sparse vector and A is sparse matrix. v is an array of dimension = number of columns in A.

void fasp_sparse_ytxbig_ (INT *jy, REAL *y, INT *nyp, REAL *x, REAL *s)

Calculates $s = y^{\wedge} t x$. y-sparse, x - no.

- void fasp_sparse_ytx_ (INT *jy, REAL *y, INT *jx, REAL *x, INT *nyp, INT *nxp, INT *icp, REAL *s)
 Calculates s = y^t x. y is sparse, x is sparse.
- void fasp_sparse_rapcmp_ (INT *ir, INT *jr, REAL *r, INT *ia, INT *ja, REAL *a, INT *ipt, INT *jpt, REAL *pt, INT *nin, INT *ncin, INT *iac, INT *jac, REAL *ac, INT *idummy)

Calculates R*A*P after the nonzero structure of the result is known. iac,jac,ac have to be allocated before call to this function.

ivector fasp_sparse_MIS (dCSRmat *A)

get the maximal independet set of a CSR matrix

9.97.1 Detailed Description

Routines for sparse matrix operations.

Note

Most algorithms work as follows: (a) Boolean operations (to determine the nonzero structure); (b) Numerical part, where the result is calculated.

: Parameter notation :1: is input; :0: is output; :10: is both

C-version: by Ludmil Zikatanov 2010-04-08 tested 2010-04-08

: Modifed Xiaozhe Hu 2010-10-18

Definition in file sparse_util.c.

9.97.2 Function Documentation

transpose a boolean matrix (only given by ia, ja)

Parameters

ia	array of row pointers (as usual in CSR)
ja	array of column indices
а	array of entries of teh input
na	number of rows of A
ma	number of cols of A
iat	array of row pointers in the result
jat	array of column indices
at	array of entries of the result

Definition at line 272 of file sparse util.c.

Multiplication of two sparse matrices: calculating the numerical values in the result.

Parameters

ia	array of row pointers 1st multiplicand
ja	array of column indices 1st multiplicand
а	entries of the 1st multiplicand
ib	array of row pointers 2nd multiplicand
jb	array of column indices 2nd multiplicand
b	entries of the 2nd multiplicand
ic	array of row pointers in c=a*b
jc	array of column indices in c=a*b
С	entries of the result: c= a*b
nap	number of rows in the 1st multiplicand
тар	number of columns in the 1st multiplicand
mbp	number of columns in the 2nd multiplicand

Modified by Chensong Zhang on 09/11/2012

Definition at line 124 of file sparse_util.c.

9.97.2.3 void fasp_sparse_abybms_ (INT * ia, INT * ja, INT * ib, INT * jb, INT * nap, INT * map, INT * map

Multiplication of two sparse matrices: calculating the nonzero structure of the result if jc is not null. If jc is null only finds num of nonzeroes.

Parameters

ia	array of row pointers 1st multiplicand
ia	array of row pointers 1st multiplicand
ja	array of column indices 1st multiplicand
ib	array of row pointers 2nd multiplicand
jb	array of column indices 2nd multiplicand
nap	number of rows of A
тар	number of cols of A
mbp	number of cols of b
ic	array of row pointers in the result (this is also computed here again, so that we can have a stand
	alone call of this routine, if for some reason the number of nonzeros in the result is known)
jc	array of column indices in the result c=a*b

Modified by Chensong Zhang on 09/11/2012

Definition at line 51 of file sparse_util.c.

9.97.2.4 void void fasp_sparse_aplbms_(INT * ia, INT * ja, INT * ib, INT * jb, INT * nab, INT * mab, INT * ic, INT * jc)

Addition of two sparse matrices: calculating the nonzero structure of the result if jc is not null. if jc is null only finds num of nonzeroes.

Parameters

ia	array of row pointers 1st summand
ia	array of row pointers 1st summand

ja	array of column indices 1st summand
ib	array of row pointers 2nd summand
jb	array of column indices 2nd summand
nab	number of rows
mab	number of cols
ic	array of row pointers in the result (this is also computed here again, so that we can have a stand
	alone call of this routine, if for some reason the number of nonzeros in the result is known)
jc	array of column indices in the result c=a+b

Definition at line 359 of file sparse_util.c.

9.97.2.5 void fasp_sparse_aplusb_ (INT *
$$ia$$
, INT * ja , REAL * a , INT * ib , INT * jb , REAL * b , INT * nab , INT * mab , INT * ic , INT * jc , REAL * c)

Addition of two sparse matrices: calculating the numerical values in the result.

Parameters

ia	array of row pointers 1st summand
ja	array of column indices 1st summand
а	entries of the 1st summand
ib	array of row pointers 2nd summand
jb	array of column indices 2nd summand
b	entries of the 2nd summand
nab	number of rows
mab	number of cols
ic	array of row pointers in c=a+b
jc	array of column indices in c=a+b
С	entries of the result: c=a+b

Definition at line 431 of file sparse_util.c.

9.97.2.6 void fasp_sparse_iit_ (INT
$$*$$
 ia, INT $*$ ja, INT $*$ na, INT $*$ ma, INT $*$ iat, INT $*$ jat)

Transpose a boolean matrix (only given by ia, ja)

Parameters

ia	array of row pointers (as usual in CSR)
ja	array of column indices
na	number of rows
ma	number of cols
iat	array of row pointers in the result
jat	array of column indices

Note

For the concrete algorithm, see:

Definition at line 197 of file sparse_util.c.

9.97.2.7 ivector fasp_sparse_MIS (dCSRmat * A)

get the maximal independet set of a CSR matrix

Parameters

Α	pointer to the matrix

Note

: only use the sparsity of A, index starts from 1 (fortran)!!

information of A

work space

return

Definition at line 913 of file sparse_util.c.

9.97.2.8 void fasp_sparse_rapcmp_(INT * ir, INT * jr, REAL * r, INT * ia, INT * ja, REAL * a, INT * ipt, INT * jpt, REAL * pt, INT * nin, INT * ncin, INT * iac, INT * jac, REAL * ac, INT * idummy)

Calculates R*A*P after the nonzero structure of the result is known. iac,jac,ac have to be allocated before call to this function.

Note

:I: is input :O: is output :IO: is both

Parameters

ir	:I: array of row pointers for R
jr	:I: array of column indices for R
r	:I: entries of R
ia	:I: array of row pointers for A
ja	:I: array of column indices for A
а	:I: entries of A
ipt	:I: array of row pointers for P
jpt	:I: array of column indices for P
pt	:I: entries of P
nin	:I: number of rows in R
ncin	:I: number of rows in
iac	:O: array of row pointers for P
jac	:O: array of column indices for P
ac	:O: entries of P
idummy	not changed

Note

compute R*A*P for known nonzero structure of the result the result is stored in iac,jac,ac!

Definition at line 791 of file sparse_util.c.

9.97.2.9 void fasp_sparse_rapms_ (INT * ir, INT * ir, INT * ia, INT * ia, INT * ip, INT * ip, INT * nin, INT * nin, INT * nin, INT * iac, INT * jac, INT * maxrout)

Calculates the nonzero structure of R*A*P, if jac is not null. If jac is null only finds num of nonzeroes.

Note

:I: is input :O: is output :IO: is both

Parameters

ir	:I: array of row pointers for R
jr	:I: array of column indices for R
ia	:I: array of row pointers for A
ja	:I: array of column indices for A
ip	:I: array of row pointers for P
jр	:I: array of column indices for P
nin	:I: number of rows in R
ncin	:I: number of columns in R
iac	:O: array of row pointers for Ac
jac	:O: array of column indices for Ac
maxrout	:O: the maximum nonzeroes per row for R

Note

Computes the sparsity pattern of R*A*P. maxrout is output and is the maximum nonzeroes per row for r. On output we also have is iac (if jac is null) and jac (if jac entry is not null). R is (n,n) A is (n,n) and P is (n,nc)!

Modified by Chensong Zhang on 09/11/2012

Definition at line 514 of file sparse_util.c.

9.97.2.10 void fasp_sparse_wta_(INT *
$$jw$$
, REAL * w , INT * ia , INT * ja , REAL * a , INT * nwp , INT * map , INT * jv , REAL * v , INT * nvp)

Calculate $v^{\wedge}t = w^{\wedge}t$ A, where w is a sparse vector and A is sparse matrix. v is an array of dimension = number of columns in A.

Note

:I: is input :O: is output :IO: is both

Parameters

jw	:I: indices such that w[jw] is nonzero
W	:I: the values of w
ia	:I: array of row pointers for A
ja	:I: array of column indices for A
а	:I: entries of A
nwp	:I: number of nonzeroes in w (the length of w)
тар	:I: number of columns in A
jv	:O: indices such that v[jv] is nonzero
V	:O: the result v^t=w^t A
nvp	:I: number of nonzeroes in v

Definition at line 651 of file sparse_util.c.

```
9.97.2.11 void fasp_sparse_wtams_ ( INT * jw, INT * ia, INT * ja, INT * nwp, INT * map, INT * jv, INT * nvp, INT * icp )
```

Finds the nonzeroes in the result of $v^t = w^t A$, where w is a sparse vector and A is sparse matrix. jv is an integer array containing the indices of the nonzero elements in the result.

:I: is input :O: is output :IO: is both

Parameters

jw	:I: indices such that w[jw] is nonzero
ia	:I: array of row pointers for A
ja	:I: array of column indices for A
nwp	:I: number of nonzeroes in w (the length of w)
тар	:I: number of columns in A
jv	:O: indices such that v[jv] is nonzero
nvp	:I: number of nonzeroes in v
icp	:IO: is a working array of length (*map) which on output satisfies icp[jv[k]-1]=k; Values of icp[] at
	positions * other than (jv[k]-1) remain unchanged.

Modified by Chensong Zhang on 09/11/2012

Definition at line 598 of file sparse_util.c.

9.97.2.12 void fasp_sparse_ytx_(INT * jy, REAL * y, INT * jx, REAL * x, INT * nyp, INT * nxp, INT * icp, REAL * s)

Calculates $s = y^{\wedge}t x$. y is sparse, x is sparse.

note::I: is input::O: is output::IO: is both

Parameters

jу	:I: indices such that y[jy] is nonzero
У	:I: is a sparse vector.
nyp	:I: number of nonzeroes in y
jx	:I: indices such that x[jx] is nonzero
X	:I: is a sparse vector.
nxp	:I: number of nonzeroes in x
icp	???
s	:O: $s = y^t x$.

Definition at line 736 of file sparse_util.c.

9.97.2.13 void fasp_sparse_ytxbig_ (INT * jy, REAL * y, INT * nyp, REAL * x, REAL * s)

Calculates $s = y^{\wedge}t x$. y-sparse, x - no.

Note

:I: is input :O: is output :IO: is both

Parameters

jy	:I: indices such that y[jy] is nonzero
у	:I: is a sparse vector.
nyp	:I: number of nonzeroes in v
X	:I: also a vector assumed to have entry for any j=jy[i]-1; for i=1:nyp. This means that x here does
	not have to be sparse.

```
s :0: s = y^{\wedge}t x.
```

Definition at line 702 of file sparse util.c.

9.98 spbcgs.c File Reference

Krylov subspace methods - Preconditioned BiCGstab with safe net.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

 INT fasp_solver_dcsr_spbcgs (dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b with safe net.

 INT fasp_solver_dbsr_spbcgs (dBSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b with safe net.

 INT fasp_solver_bdcsr_spbcgs (block_dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b with safe net.

 INT fasp_solver_dstr_spbcgs (dSTRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop type, const SHORT print level)

Preconditioned BiCGstab method for solving Au=b with safe net.

9.98.1 Detailed Description

Krylov subspace methods - Preconditioned BiCGstab with safe net. Abstract algorithm

PBICGStab method to solve A*x=b is to generate {x k} to approximate x

Note: We generate a series of $\{p_k\}$ such that $V_k=\text{span}\{p_1,...,p_k\}$.

```
Step 0. Given A, b, x 0, M
```

Step 1. Compute residual $r_0 = b-A*x_0$ and convergence check;

```
Step 2. Initialization z_0 = M^{(-1)}*r_0, p_0=z_0;
```

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r k,z k,p k);
- update solution: x_{k+1} = x_k + alpha*p_k;
- · check whether x is NAN:
- · perform stagnation check;

- update residual: r_{k+1} = r_k alpha*(A*p_k);
- if $r_{k+1} < r_{best}$: save x_{k+1} as x_{best} ;
- · perform residual check;
- obtain p_{k+1} using {p_0, p_1, ..., p_k};
- · prepare for next iteration;
- · print the result of k-th iteration; END FOR

Convergence check: norm(r)/norm(b) < tol

Stagnation check:

- IF $norm(alpha*p_k)/norm(x_{k+1}) < tol_stag$
 - 1. compute $r=b-A*x \{k+1\}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Stag_Check) restart;
- END IF

Residual check:

- IF $norm(r_{k+1})/norm(b) < tol$
 - 1. compute the real residual $r = b-A*x_{k+1}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Res_Check) restart;
- END IF

Safe net check:

- IF $r_{k+1} > r_{best}$
 - 1. $x_{k+1} = x_{best}$
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See spbcgs.c for a safer version

Definition in file spbcgs.c.

9.98.2 Function Documentation

9.98.2.1 INT fasp_solver_bdcsr_spbcgs (block_dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b with safe net.

Parameters

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

03/31/2013

Definition at line 868 of file spbcgs.c.

9.98.2.2 INT fasp_solver_dbsr_spbcgs (dBSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b with safe net.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

03/31/2013

Definition at line 480 of file spbcgs.c.

9.98.2.3 INT fasp_solver_dcsr_spbcgs (dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b with safe net.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

03/31/2013

Definition at line 92 of file spbcgs.c.

9.98.2.4 INT fasp_solver_dstr_spbcgs (dSTRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned BiCGstab method for solving Au=b with safe net.

Parameters

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

03/31/2013

Definition at line 1256 of file spbcgs.c.

9.99 spcg.c File Reference

Krylov subspace methods – Preconditioned conjugate gradient with safe net.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

INT fasp_solver_dcsr_spcg (dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient method for solving Au=b with safe net.

 INT fasp_solver_bdcsr_spcg (block_dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient method for solving Au=b with safe net.

INT fasp_solver_dstr_spcg (dSTRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient method for solving Au=b with safe net.

9.99.1 Detailed Description

Krylov subspace methods – Preconditioned conjugate gradient with safe net. Abstract algorithm

PCG method to solve A*x=b is to generate $\{x_k\}$ to approximate x

```
Step 0. Given A, b, x_0, M
```

Step 1. Compute residual $r_0 = b-A*x_0$ and convergence check;

```
Step 2. Initialization z 0 = M^{-1}*r 0, p 0=z 0;
```

Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r_k,z_k,p_k);
- update solution: x_{k+1} = x_k + alpha*p_k;
- · check whether x is NAN;
- · perform stagnation check;
- update residual: $r_{k+1} = r_k alpha*(A*p_k)$;
- if r_{k+1} < r_{best}: save x_{k+1} as x_{best};
- · perform residual check;
- obtain p_{k+1} using {p_0, p_1, ..., p_k};
- · prepare for next iteration;
- print the result of k-th iteration; END FOR

Convergence check: norm(r)/norm(b) < tol

Stagnation check:

- IF norm(alpha*p_k)/norm(x_{k+1}) < tol_stag
 - 1. compute $r=b-A*x_{k+1}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Stag_Check) restart;
- END IF

Residual check:

- IF $norm(r_{k+1})/norm(b) < tol$
 - 1. compute the real residual $r = b-A*x_{k+1}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Res_Check) restart;
- END IF

Safe net check:

- IF $r_{k+1} > r_{best}$
 - 1. $x_{k+1} = x_{best}$
- END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See pcg.c for a version without safe net

Definition in file spcg.c.

9.99.2 Function Documentation

9.99.2.1 INT fasp_solver_bdcsr_spcg (block_dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient method for solving Au=b with safe net.

Parameters

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)

tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

03/28/2013

Definition at line 414 of file spcg.c.

9.99.2.2 INT fasp_solver_dcsr_spcg (dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient method for solving Au=b with safe net.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

03/28/2013

Definition at line 89 of file spcg.c.

9.99.2.3 INT fasp_solver_dstr_spcg (dSTRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

Preconditioned conjugate gradient method for solving Au=b with safe net.

Parameters

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
MaxIt	Maximal number of iterations
tol	Tolerance for stopping
рс	Pointer to the structure of precondition (precond)
print_level	How much information to print out
stop_type	Stopping criteria type

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

03/28/2013

Definition at line 738 of file spcg.c.

9.100 spgmres.c File Reference

Krylov subspace methods - Preconditioned GMRes with safe net.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

 INT fasp_solver_dcsr_spgmres (dCSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b with safe-guard.

 INT fasp_solver_bdcsr_spgmres (block_dCSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b with safe-guard.

 INT fasp_solver_dbsr_spgmres (dBSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b with safe-guard.

 INT fasp_solver_dstr_spgmres (dSTRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b with safe-guard.

9.100.1 Detailed Description

Krylov subspace methods - Preconditioned GMRes with safe net.

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See also pgmres.c for a variable restarting version. See pgmres.c for a version without safe net

Definition in file spgmres.c.

9.100.2 Function Documentation

9.100.2.1 INT fasp_solver_bdcsr_spgmres (block_dCSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b with safe-guard.

Parameters

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/05/2013

Definition at line 387 of file spgmres.c.

9.100.2.2 INT fasp_solver_dbsr_spgmres (dBSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b with safe-guard.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/05/2013

Definition at line 728 of file spgmres.c.

9.100.2.3 INT fasp_solver_dcsr_spgmres (dCSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b with safe-guard.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/05/2013 Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate

Definition at line 46 of file spgmres.c.

9.100.2.4 INT fasp_solver_dstr_spgmres (dSTRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop type, const SHORT print level)

Preconditioned GMRES method for solving Au=b with safe-guard.

Parameters

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/05/2013

Definition at line 1069 of file spgmres.c.

9.101 spminres.c File Reference

Krylov subspace methods - Preconditioned minimal residual with safe net.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

 INT fasp_solver_dcsr_spminres (dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b with safe net.

• INT fasp_solver_bdcsr_spminres (block_dCSRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop type, const SHORT print level)

A preconditioned minimal residual (Minres) method for solving Au=b with safe net.

 INT fasp_solver_dstr_spminres (dSTRmat *A, dvector *b, dvector *u, precond *pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b with safe net.

9.101.1 Detailed Description

Krylov subspace methods - Preconditioned minimal residual with safe net. Abstract algorithm

 $Krylov \ method \ to \ solve \ A*x=b \ is \ to \ generate \ \{x_k\} \ to \ approximate \ x, \ where \ x_k \ is \ the \ optimal \ solution \ in \ Krylov \ space$

$$V_k=span\{r_0,A*r_0,A^2*r_0,...,A^{k-1}*r_0\},$$

under some inner product.

For the implementation, we generate a series of {p_k} such that V_k=span{p_1,...,p_k}. Details:

- Step 0. Given A, b, x_0, M
- Step 1. Compute residual $r_0 = b-A*x_0$ and convergence check;
- Step 2. Initialization $z_0 = M^{-1}*r_0$, $p_0=z_0$;
- Step 3. Main loop ...

FOR k = 0:MaxIt

- get step size alpha = f(r k,z k,p k);
- update solution: $x_{k+1} = x_k + alpha*p_k$;
- check whether x is NAN;
- · perform stagnation check;
- update residual: r_{k+1} = r_k alpha*(A*p_k);
- if r_{k+1} < r_{best}: save x_{k+1} as x_{best};
- · perform residual check;
- obtain p_{k+1} using {p_0, p_1, ..., p_k};
- · prepare for next iteration;
- · print the result of k-th iteration; END FOR

Convergence check: norm(r)/norm(b) < tol

Stagnation check:

- IF norm(alpha*p_k)/norm(x_{k+1}) < tol_stag
 - 1. compute $r=b-A*x_{k+1}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Stag_Check) restart;
- END IF

Residual check:

- IF $norm(r_{k+1})/norm(b) < tol$
 - 1. compute the real residual $r = b-A*x_{k+1}$;
 - 2. convergence check;
 - 3. IF (not converged & restart_number < Max_Res_Check) restart;

• END IF

Safe net check:

• IF $r_{k+1} > r_{best}$

1.
$$x_{k+1} = x_{best}$$

• END IF

Note

Refer to Y. Saad 2003 Iterative methods for sparse linear systems (2nd Edition), SIAM See pminres.c for a version without safe net

Definition in file spminres.c.

9.101.2 Function Documentation

9.101.2.1 INT fasp_solver_bdcsr_spminres (block_dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b with safe net.

Parameters

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
U	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/09/2013

Definition at line 543 of file spminres.c.

9.101.2.2 INT fasp_solver_dcsr_spminres (dCSRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b with safe net.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/09/2013

Definition at line 96 of file spminres.c.

9.101.2.3 INT fasp_solver_dstr_spminres (dSTRmat * A, dvector * b, dvector * u, precond * pc, const REAL tol, const INT MaxIt, const SHORT stop_type, const SHORT print_level)

A preconditioned minimal residual (Minres) method for solving Au=b with safe net.

Parameters

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
и	Pointer to dvector: the unknowns
MaxIt	Maximal number of iterations
tol	Tolerance for stopping
рс	Pointer to the structure of precondition (precond)
print_level	How much information to print out
stop_type	Stopping criteria type

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/09/2013

Definition at line 990 of file spminres.c.

9.102 spvgmres.c File Reference

Krylov subspace methods - Preconditioned variable-restart GMRes with safe net.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
#include "itsolver_util.inl"
```

Functions

 INT fasp_solver_dcsr_spvgmres (dCSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

INT fasp_solver_bdcsr_spvgmres (block_dCSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b.

 INT fasp_solver_dbsr_spvgmres (dBSRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

 INT fasp_solver_dstr_spvgmres (dSTRmat *A, dvector *b, dvector *x, precond *pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

9.102.1 Detailed Description

Krylov subspace methods - Preconditioned variable-restart GMRes with safe net.

Note

Refer to A.H. Baker, E.R. Jessup, and Tz.V. Kolev A Simple Strategy for Varying the Restart Parameter in GMRE-S(m) Journal of Computational and Applied Mathematics, 230 (2009) pp. 751-761. UCRL-JRNL-235266. See pvgmres.c a version without safe net

Definition in file spvgmres.c.

9.102.2 Function Documentation

9.102.2.1 INT fasp_solver_bdcsr_spvgmres (block_dCSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Preconditioned GMRES method for solving Au=b.

Parameters

Α	Pointer to block_dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/06/2013

Definition at line 427 of file spygmres.c.

9.102.2.2 INT fasp_solver_dbsr_spvgmres (dBSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

Parameters

Α	Pointer to dBSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/06/2013

Definition at line 807 of file spvgmres.c.

9.102.2.3 INT fasp_solver_dcsr_spvgmres (dCSRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

Parameters

Α	Pointer to dCSRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type
print_level	How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/06/2013 Modified by Chunsheng Feng on 07/22/2013: Add adapt memory allocate

Definition at line 49 of file spvgmres.c.

9.102.2.4 INT fasp_solver_dstr_spvgmres (dSTRmat * A, dvector * b, dvector * x, precond * pc, const REAL tol, const INT MaxIt, SHORT restart, const SHORT stop_type, const SHORT print_level)

Solve "Ax=b" using PGMRES(right preconditioned) iterative method in which the restart parameter can be adaptively modified during the iteration.

Parameters

Α	Pointer to dSTRmat: the coefficient matrix
b	Pointer to dvector: the right hand side
X	Pointer to dvector: the unknowns
рс	Pointer to the structure of precondition (precond)
tol	Tolerance for stopping
MaxIt	Maximal number of iterations
restart	Restarting steps
stop_type	Stopping criteria type

print level How much information to print out

Returns

Number of iterations if converged, error message otherwise

Author

Chensong Zhang

Date

04/06/2013

Definition at line 1187 of file spvgmres.c.

9.103 threads.c File Reference

Get and set number of threads and assigne work load for each thread.

```
#include <stdio.h>
#include <stdlib.h>
#include "fasp.h"
```

Functions

• void FASP_GET_START_END (INT procid, INT nprocs, INT n, INT *start, INT *end)

Assign Load to each thread.

9.103.1 Detailed Description

Get and set number of threads and assigne work load for each thread.

Definition in file threads.c.

9.103.2 Function Documentation

```
9.103.2.1 void FASP_GET_START_END ( INT procid, INT nprocs, INT n, INT * start, INT * end )
```

Assign Load to each thread.

Parameters

	procid	Index of thread
ĺ	nprocs	Number of threads

n	Total workload
start	Pointer to the begin of each thread in total workload
end	Pointer to the end of each thread in total workload

Author

Chunsheng Feng, Xiaoqiang Yue and Zheng Li

Date

June/25/2012

Definition at line 83 of file threads.c.

9.104 timing.c File Reference

Timing subroutines.

```
#include <time.h>
#include "fasp_functs.h"
#include "fasp.h"
```

Functions

• void fasp_gettime (REAL *time)

Get system time.

9.104.1 Detailed Description

Timing subroutines.

Definition in file timing.c.

9.104.2 Function Documentation

```
9.104.2.1 fasp_gettime ( REAL * time )
```

Get system time.

Author

Chunsheng Feng, Zheng LI

Date

11/10/2012

Definition at line 28 of file timing.c.

9.105 vec.c File Reference

Simple operations for vectors.

```
#include <math.h>
#include "fasp.h"
#include "fasp_functs.h"
```

Functions

INT fasp dvec isnan (dvector *u)

Check a dvector whether there is NAN.

dvector fasp dvec create (const INT m)

Create dvector data space of REAL type.

ivector fasp_ivec_create (const INT m)

Create vector data space of INT type.

void fasp_dvec_alloc (const INT m, dvector *u)

Create dvector data space of REAL type.

void fasp ivec alloc (const INT m, ivector *u)

Create vector data space of INT type.

void fasp_dvec_free (dvector *u)

Free vector data space of REAL type.

void fasp_ivec_free (ivector *u)

Free vector data space of INT type.

void fasp_dvec_null (dvector *x)

Initialize dvector.

void fasp dvec rand (const INT n, dvector *x)

Generate random REAL vector in the range from 0 to 1.

void fasp_dvec_set (INT n, dvector *x, REAL val)

Initialize dvector x[i]=val for i=0:n-1.

void fasp_ivec_set (const INT m, ivector *u)

Set ivector value to be m.

void fasp_dvec_cp (dvector *x, dvector *y)

Copy dvector x to dvector y.

REAL fasp_dvec_maxdiff (dvector *x, dvector *y)

Maximal difference of two dvector x and y.

void fasp_dvec_symdiagscale (dvector *b, dvector *diag)

Symmetric diagonal scaling D^{\land} {-1/2}b.

9.105.1 Detailed Description

Simple operations for vectors.

Note

Every structures should be initialized before usage.

Definition in file vec.c.

9.105 vec.c File Reference 411

9.105.2 Function Documentation

9.105.2.1 void fasp_dvec_alloc (const INT m, dvector *u)

Create dvector data space of REAL type.

Parameters

m	Number of rows
и	Pointer to dvector (OUTPUT)

Author

Chensong Zhang

Date

2010/04/06

Definition at line 99 of file vec.c.

9.105.2.2 void fasp_dvec_cp (dvector * x, dvector * y)

Copy dvector x to dvector y.

Parameters

X	Pointer to dvector
у	Pointer to dvector (MODIFIED)

Author

Chensong Zhang

Date

11/16/2009

Definition at line 345 of file vec.c.

9.105.2.3 dvector fasp_dvec_create (const INT m)

Create dvector data space of REAL type.

Parameters

m	Number of rows

Returns

u The new dvector

Author Chensong Zhang Date 2010/04/06 Definition at line 56 of file vec.c. 9.105.2.4 void fasp_dvec_free (dvector * u) Free vector data space of REAL type. **Parameters** Pointer to dvector which needs to be deallocated **Author** Chensong Zhang Date 2010/04/03 Definition at line 139 of file vec.c. 9.105.2.5 INT fasp_dvec_isnan (dvector * u) Check a dvector whether there is NAN. **Parameters** Pointer to dvector Returns Return TRUE if there is NAN **Author** Chensong Zhang Date 2013/03/31 Definition at line 33 of file vec.c.

9.105.2.6 REAL fasp_dvec_maxdiff (dvector * x, dvector * y)

Maximal difference of two dvector x and y.

Generated on Thu Dec 26 2013 21:01:41 for Fast Auxiliary Space Preconditioning by Doxygen

9.105 vec.c File Reference 413

Parameters

Х	Pointer to dvector
У	Pointer to dvector

Returns

Maximal norm of x-y

Author

Chensong Zhang

Date

11/16/2009

Modified by chunsheng Feng, Zheng Li

Date

06/30/2012

Definition at line 368 of file vec.c.

9.105.2.7 void fasp_dvec_null (dvector * x)

Initialize dvector.

Parameters

X	Pointer to dvector which needs to be initialized
---	--

Author

Chensong Zhang

Date

2010/04/03

Definition at line 177 of file vec.c.

9.105.2.8 void fasp_dvec_rand (const INT n, dvector * x)

Generate random REAL vector in the range from 0 to 1.

Parameters

n	Size of the vector
X	Pointer to dvector

Note

Sample usage:

dvector xapp;

fasp_dvec_create(100,&xapp);

fasp_dvec_rand(100,&xapp);

fasp_dvec_print(100,&xapp);

Author

Chensong Zhang

Date

11/16/2009

Definition at line 203 of file vec.c.

9.105.2.9 void fasp_dvec_set (INT n, dvector * x, REAL val)

Initialize dvector x[i]=val for i=0:n-1.

Parameters

n	Number of variables
Х	Pointer to dvector
val	Initial value for the vector

Author

Chensong Zhang

Date

11/16/2009

Modified by Chunsheng Feng, Xiaoqiang Yue on 05/23/2012

Definition at line 235 of file vec.c.

9.105.2.10 void fasp_dvec_symdiagscale (dvector * b, dvector * diag)

Symmetric diagonal scaling $D^{-1/2}b$.

9.105 vec.c File Reference 415

Parameters

b	Pointer to dvector
diag	Pointer to dvector: the diagonal entries

Author

Xiaozhe Hu

Date

01/31/2011

Definition at line 421 of file vec.c.

9.105.2.11 void fasp_ivec_alloc (const INT m, ivector *u)

Create vector data space of INT type.

Parameters

m	Number of rows
и	Pointer to ivector (OUTPUT)

Author

Chensong Zhang

Date

2010/04/06

Definition at line 119 of file vec.c.

9.105.2.12 ivector fasp_ivec_create (const INT m)

Create vector data space of INT type.

Parameters

m	Number of rows
---	----------------

Returns

u The new ivector

Author

Chensong Zhang

Date

2010/04/06

Definition at line 78 of file vec.c.

9.105.2.13 void fasp_ivec_free (ivector *u)

Free vector data space of INT type.

Parameters

И	Pointer to ivector which needs to be deallocated
u	Total to Woods Which hoods to be dedinedated

Author

Chensong Zhang

Date

2010/04/03

Note

This function is same as fasp_dvec_free except input type.

Definition at line 159 of file vec.c.

```
9.105.2.14 void fasp_ivec_set ( const INT m, ivector * u )
```

Set ivector value to be m.

Parameters

т	Integer value of ivector
и	Pointer to ivector (MODIFIED)

Author

Chensong Zhang

Date

04/03/2010

Modified by Chunsheng Feng, Xiaoqiang Yue

Date

05/23/2012

Definition at line 304 of file vec.c.

9.106 wrapper.c File Reference

Wrappers for accessing functions by advanced users.

```
#include "fasp.h"
#include "fasp_block.h"
#include "fasp_functs.h"
```

Functions

void fasp_fwrapper_amg_ (INT *n, INT *nnz, INT *ia, INT *ja, REAL *a, REAL *b, REAL *u, REAL *tol, INT *maxit, INT *ptrlvl)

Solve Ax=b by Ruge and Stuben's classic AMG.

void fasp_fwrapper_krylov_amg_ (INT *n, INT *nnz, INT *ia, INT *ja, REAL *a, REAL *b, REAL *u, REAL *tol, INT *maxit, INT *ptrlvl)

Solve Ax=b by Krylov method preconditioned by classic AMG.

INT fasp_wrapper_dbsr_krylov_amg (INT n, INT nnz, INT nb, INT *ia, INT *ja, REAL *a, REAL *b, REAL *u, REAL tol, INT maxit, INT ptrlvl)

Solve Ax=b by Krylov method preconditioned by AMG (dcsr - > dbsr)

INT fasp_wrapper_dcoo_dbsr_krylov_amg (INT n, INT nnz, INT nb, INT *ia, INT *ja, REAL *a, REAL *b, REAL
 *u, REAL tol, INT maxit, INT ptrlvl)

Solve Ax=b by Krylov method preconditioned by AMG (dcoo - > dbsr)

9.106.1 Detailed Description

Wrappers for accessing functions by advanced users.

Note

Input variables should not need fasp.h!!!

Definition in file wrapper.c.

9.106.2 Function Documentation

9.106.2.1 void void fasp_fwrapper_amg_ (INT * n, INT * n, INT * ia, INT * ja, REAL * a, REAL * b, REAL * u, REAL * tol, INT * maxit, INT * ptrlvl)

Solve Ax=b by Ruge and Stuben's classic AMG.

Parameters

n	Number of cols of A
nnz	Number of nonzeros of A
ia	IA of A in CSR format
ja	JA of A in CSR format
а	VAL of A in CSR format
b	RHS vector
и	Solution vector
tol	Tolerance for iterative solvers
maxit	Max num of iterations
ptrlvl	Print level for iterative solvers

Author

Chensong Zhang

Date

09/16/2010

Definition at line 37 of file wrapper.c.

9.106.2.2 void fasp_fwrapper_krylov_amg_ (INT * n, INT * n, INT * ia, INT * ja, REAL * a, REAL * b, REAL * u, REAL * u,

Solve Ax=b by Krylov method preconditioned by classic AMG.

Parameters

n	Number of cols of A
nnz	Number of nonzeros of A
ia	IA of A in CSR format
ja	JA of A in CSR format
а	VAL of A in CSR format
b	RHS vector
и	Solution vector
tol	Tolerance for iterative solvers
maxit	Max num of iterations
ptrlvl	Print level for iterative solvers

Author

Chensong Zhang

Date

09/16/2010

Definition at line 87 of file wrapper.c.

9.106.2.3 INT fasp_wrapper_dbsr_krylov_amg (INT n, INT n), INT n, INT n, INT n, INT n), INT n, REAL n0, REAL n0, REAL n0, INT n0, IN

Solve Ax=b by Krylov method preconditioned by AMG (dcsr - > dbsr)

Parameters

n	Number of cols of A
nnz	Number of nonzeros of A
nb	Size of each small block
ia	IA of A in CSR format
ja	JA of A in CSR format
а	VAL of A in CSR format
b	RHS vector
и	Solution vector
tol	Tolerance for iterative solvers
maxit	Max num of iterations
ptrlvl	Print level for iterative solvers

Author

Xiaozhe Hu

Date

03/05/2013

Definition at line 142 of file wrapper.c.

9.106.2.4 INT fasp_wrapper_dcoo_dbsr_krylov_amg (INT n, INT n, INT nb, INT * ia, INT * ia, REAL * a, REAL *

Solve Ax=b by Krylov method preconditioned by AMG (dcoo - > dbsr)

Parameters

n	Number of cols of A
nnz	Number of nonzeros of A
nb	Size of each small block
ia	IA of A in COO format
ja	JA of A in COO format
а	VAL of A in COO format
b	RHS vector
и	Solution vector
tol	Tolerance for iterative solvers
maxit	Max num of iterations
ptrlvl	Print level for iterative solvers

Author

Xiaozhe Hu

Date

03/06/2013

Definition at line 226 of file wrapper.c.

Index

FASP HEADER	input_param, 41
fasp.h, 144	AMG_schwarz_levels
	input param, 41
A	AMG_smooth_filter
precond_block_data, 48	input param, 41
precond_FASP_blkoil_data, 59	AMG_smooth_order
ABS	input_param, 41
fasp.h, 144	AMG_smoother
AMG_ILU_levels	input_param, 41
input_param, 39	AMG_strong_coupled
AMG_aggressive_level	input_param, 41
input_param, 39	AMG_strong_threshold
AMG_aggressive_path	input_param, 41
input_param, 39	AMG_tentative_smooth
AMG_amli_degree	input_param, 41
input_param, 39	AMG tol
AMG_coarse_dof	input param, 41
input_param, 39	AMG_truncation_threshold
AMG_coarse_scaling	input_param, 42
input_param, 39	• —
AMG_coarsening_type	AMG_type
input_param, 39	input_param, 42
AMG_cycle_type	AMLI_CYCLE
input_param, 39	messages.h, 234
AMG_data, 19	ASCEND
AMG_data_bsr, 20	messages.h, 234
AMG_interpolation_type	Aarray
input_param, 40	precond_block_data, 48
AMG_levels	Ablock
input_param, 40	precond_block_data, 48
AMG_max_aggregation	amg.c, 65
input_param, 40	fasp_solver_amg, 65
AMG_max_row_sum	amg_setup_aggregation_bsr.inl, 66
input_param, 40	amg_setup_aggregation_csr.inl, 66
AMG_maxit	amg_setup_cr.c, 66
input_param, 40	fasp_amg_setup_cr, 67
AMG_nl_amli_krylov_type	amg_setup_rs.c, 67
input_param, 40	fasp_amg_setup_rs, 68
AMG_param, 21	fasp_amg_setup_rs_omp, 68
AMG polynomial degree	amg_setup_sa.c, 69
input_param, 40	fasp_amg_setup_sa, 69
AMG_postsmooth_iter	amg_setup_ua.c, 70
input_param, 40	fasp_amg_setup_ua, 71
AMG presmooth iter	fasp_amg_setup_ua_bsr, 71
input_param, 40	amg solve.c, 71
AMG relaxation	fasp amg solve, 72

fasp_amg_solve_amli, 72	fasp_blas_dcsr_rap_agg1, 100
fasp_amg_solve_nl_amli, 73	fasp_blas_dcsr_vmv, 101
fasp_famg_solve, 73	blas_csrl.c, 101
amgparam	fasp_blas_dcsrl_mxv, 102
precond_block_data, 49	blas_smat.c, 102
amlirecur.c, 74	fasp_blas_array_axpy_nc2, 104
fasp_amg_amli_coef, 75	fasp_blas_array_axpy_nc3, 104
fasp_solver_amli, 76	fasp_blas_array_axpy_nc5, 105
fasp_solver_nl_amli, 76	fasp_blas_array_axpy_nc7, 105
fasp_solver_nl_amli_bsr, 77	fasp_blas_array_axpyz_nc2, 105
array.c, 77	fasp_blas_array_axpyz_nc3, 106
fasp_array_cp, 78	fasp_blas_array_axpyz_nc5, 106
fasp_array_cp_nc3, 78	fasp_blas_array_axpyz_nc7, 107
fasp_array_cp_nc5, 79	fasp_blas_smat_aAxpby, 107
fasp_array_cp_nc7, 79	fasp_blas_smat_mul, 108
fasp_array_null, 79	fasp_blas_smat_mul_nc2, 108
fasp_array_set, 80	fasp_blas_smat_mul_nc3, 109
fasp_iarray_cp, 80	fasp_blas_smat_mul_nc5, 109
fasp_iarray_set, 81	fasp_blas_smat_mul_nc7, 109
	fasp_blas_smat_mxv, 110
BIGREAL	fasp_blas_smat_mxv_nc2, 110
fasp.h, 145	fasp_blas_smat_mxv_nc3, 110
blas_array.c, 81	fasp_blas_smat_mxv_nc5, 112
fasp_blas_array_ax, 82	fasp blas smat mxv nc7, 112
fasp_blas_array_axpby, 82	fasp_blas_smat_ymAx, 112
fasp_blas_array_axpy, 83	fasp_blas_smat_ymAx_nc2, 114
fasp_blas_array_axpyz, 83	fasp_blas_smat_ymAx_nc3, 114
fasp_blas_array_dotprod, 84	fasp_blas_smat_ymAx_nc5, 115
fasp_blas_array_norm1, 84	fasp_blas_smat_ymAx_nc7, 115
fasp_blas_array_norm2, 85	fasp_blas_smat_ymAx_ns, 116
fasp_blas_array_norminf, 85	fasp_blas_smat_ymAx_ns2, 116
blas_bcsr.c, 86	fasp_blas_smat_ymAx_ns3, 117
fasp_blas_bdbsr_aAxpy, 87	fasp_blas_smat_ymAx_ns5, 117
fasp_blas_bdbsr_mxv, 88	fasp_blas_smat_ymAx_ns7, 118
fasp_blas_bdcsr_aAxpy, 88	fasp_blas_smat_ypAx, 118
fasp_blas_bdcsr_mxv, 88	fasp_blas_smat_ypAx_nc2, 119
blas_bsr.c, 89	fasp_blas_smat_ypAx_nc3, 119
fasp_blas_dbsr_aAxpby, 90	fasp_blas_smat_ypAx_nc5, 119
fasp_blas_dbsr_aAxpy, 91	fasp_blas_smat_ypAx_nc7, 121
fasp_blas_dbsr_mxv, 91	blas_str.c, 121
fasp_blas_dbsr_rap, 93	fasp_blas_dstr_aAxpy, 122
fasp_blas_dbsr_rap1, 93	fasp_blas_dstr_mxv, 122
blas_csr.c, 94	fasp_dstr_diagscale, 122
fasp_blas_dcsr_aAxpy, 95	blas_vec.c, 123
fasp_blas_dcsr_aAxpy_agg, 95	fasp_blas_dvec_axpy, 124
fasp_blas_dcsr_add, 96	fasp_blas_dvec_axpyz, 124
fasp_blas_dcsr_axm, 96	fasp_blas_dvec_dotprod, 124
fasp_blas_dcsr_mxm, 97	fasp_blas_dvec_norm1, 125
fasp_blas_dcsr_mxv, 97	fasp_blas_dvec_norm2, 125
fasp_blas_dcsr_mxv_agg, 98	fasp_blas_dvec_norminf, 126
fasp_blas_dcsr_ptap, 98	fasp_blas_dvec_relerr, 126
fasp_blas_dcsr_rap, 99	block_BSR, 23
fasp_blas_dcsr_rap4, 99	fasp_block.h, 152
fasp_blas_dcsr_rap_agg, 100	block_Reservoir, 26

fasp_block.h, 152	fasp.h, 149
block_dCSRmat, 24	dCSRmat, 29
fasp_block.h, 152	fasp.h, 149
block_dvector, 25	dCSRmat2SAMGInput
fasp_block.h, 152	interface_samg.c, 179
block_iCSRmat, 25	DEBUG MODE
fasp_block.h, 152	fasp.h, 145
block_ivector, 26	DESCEND
fasp_block.h, 152	messages.h, 235
7—	DIAGONAL_PREF
C2N	fasp.h, 145
fasp.h, 145	DLMALLOC
CF_ORDER	fasp.h, 145
messages.h, 234	dSTRmat, 31
CGPT	fasp.h, 149
messages.h, 234	ddenmat, 30
CHMEM_MODE	fasp.h, 149
fasp.h, 145	•
CLASSIC AMG	diag
messages.h, 234	precond_block_reservoir_data, 51
COARSE AC	diaginv
messages.h, 234	precond_block_reservoir_data, 51
COARSE CR	precond_FASP_blkoil_data, 59
messages.h, 234	diaginv_S
COARSE RS	precond_FASP_blkoil_data, 60
messages.h, 235	diaginv_noscale
CPFIRST	precond_FASP_blkoil_data, 60
messages.h, 235	diaginvS
checkmat.c, 127	precond_block_reservoir_data, 51
fasp_check_dCSRmat, 128	doxygen.h, 139
fasp_check_diagdom, 128	dvector, 31
fasp_check_diagpos, 128	fasp.h, 149
fasp check diagzero, 130	dvector2SAMGInput
fasp check iCSRmat, 130	interface_samg.c, 179
fasp_check_symm, 130	
coarsening_cr.c, 132	е
fasp_amg_coarsening_cr, 132	grid2d, 33
coarsening rs.c, 133	ERROR_ALLOC_MEM
fasp_amg_coarsening_rs, 134	messages.h, 235
col idx	ERROR_AMG_COARSEING
precond_block_data, 49	messages.h, 235
convert.c, 135	ERROR_DATA_ZERODIAG
endian_convert_int, 136	messages.h, 236
endian_convert_real, 136	ERROR_DUMMY_VAR
fasp_aux_bbyteToldouble, 136	messages.h, 236
fasp_aux_change_endian4, 138	ERROR_INPUT_PAR
fasp aux change endian8, 138	messages.h, 236
iasp_aux_oriariye_eriolario, 130	ERROR MISC
dBSRmat, 27	messages.h, 236
fasp_block.h, 152	ERROR NUM BLOCKS
JA, 27	messages.h, 236
val, 27	ERROR OPEN FILE
dCOOmat, 28	messages.h, 236
fasp.h, 149	ERROR QUAD DIM
dCSRLmat, 29	messages.h, 236

ERROR_QUAD_TYPE	DIAGONAL PREF, 145
messages.h, 237	DLMALLOC, 145
ERROR_REGRESS	dSTRmat, 149
messages.h, 237	ddenmat, 149
-	
ERROR_SOLVER_EXIT	dvector, 149
messages.h, 237	FASP_GSRB, 145
ERROR_SOLVER_MAXIT	FASP_USE_ILU, 145
messages.h, 237	GE, 146
ERROR_SOLVER_MISC	GT, 146
messages.h, 237	grid2d, 149
ERROR SOLVER STAG	iCOOmat, 149
messages.h, 237	iCSRmat, 149
ERROR_SOLVER_TYPE	IMAP, 150
messages.h, 238	INT, 146
-	
ERROR_WRONG_FILE	ISNAN, 146
messages.h, 238	ISTART, 146
edges	idenmat, 149
grid2d, 33	ivector, 149
ediri	LE, 146
grid2d, 33	LONG, 146
efather	LONGLONG, 146
grid2d, 33	LS, 147
eigen.c, 139	LinkList, 149
fasp_dcsr_eig, 139	ListElement, 150
· — — •	MAX, 147
endian_convert_int	•
convert.c, 136	MAX_AMG_LVL, 147
endian_convert_real	MAX_REFINE_LVL, 147
convert.c, 136	MAX_RESTART, 147
	MAX_STAG, 147
FALSE	MAXIMAP, 150
messages.h, 238	MIN, 147
FASP_GET_START_END	N2C, 147
threads.c, 408	NEDMALLOC, 148
FASP GSRB	nx_rb, 150
fasp.h, 145	ny_rb, 150
FASP USE ILU	nz rb, 150
fasp.h, 145	OPENMP_HOLDS, 148
FGPT	pcgrid2d, 150
= -	
messages.h, 238	pgrid2d, 150
FPFIRST	REAL, 148
messages.h, 238	RS_C1, 148
factor.f, 140	SHORT, 148
famg.c, 140	SMALLREAL, 148
fasp_solver_famg, 141	STAG_RATIO, 148
fasp.h, 141	total_alloc_count, 150
FASP_HEADER, 144	total_alloc_mem, 150
ABS, 144	fasp BinarySearch
BIGREAL, 145	ordering.c, 255
C2N, 145	fasp_amg_amli_coef
CHMEM_MODE, 145	amlirecur.c, 75
dCOOmat, 149	fasp_amg_coarsening_cr
dCSRLmat, 149	coarsening_cr.c, 132
dCSRmat, 149	fasp_amg_coarsening_rs
DEBUG_MODE, 145	coarsening_rs.c, 134

fasp_amg_data_bsr_create	fasp_aux_dQuickSortIndex
init.c, 173	ordering.c, 252
fasp_amg_data_bsr_free	fasp_aux_givens
init.c, 173	givens.c, 159
fasp_amg_data_create	fasp_aux_iQuickSort
init.c, 174	ordering.c, 252
fasp_amg_data_free	fasp_aux_iQuickSortIndex
init.c, 174	ordering.c, 253
fasp_amg_interp	fasp_aux_merge
interpolation.c, 182	ordering.c, 253
fasp_amg_interp1	fasp_aux_msort
interpolation.c, 183	ordering.c, 254
fasp_amg_interp_em	fasp_aux_unique
interpolation_em.c, 184	ordering.c, 254
· —	-
fasp_amg_interp_trunc	fasp_blas_array_ax
interpolation.c, 183	blas_array.c, 82
fasp_amg_setup_cr	fasp_blas_array_axpby
amg_setup_cr.c, 67	blas_array.c, 82
fasp_amg_setup_rs	fasp_blas_array_axpy
amg_setup_rs.c, 68	blas_array.c, 83
fasp_amg_setup_rs_omp	fasp_blas_array_axpy_nc2
amg_setup_rs.c, 68	blas_smat.c, 104
fasp_amg_setup_sa	fasp_blas_array_axpy_nc3
amg_setup_sa.c, 69	blas_smat.c, 104
fasp_amg_setup_ua	fasp_blas_array_axpy_nc5
amg_setup_ua.c, 71	blas_smat.c, 105
fasp_amg_setup_ua_bsr	fasp_blas_array_axpy_nc7
amg_setup_ua.c, 71	blas_smat.c, 105
fasp_amg_solve	fasp_blas_array_axpyz
amg_solve.c, 72	blas_array.c, 83
fasp_amg_solve_amli	fasp_blas_array_axpyz_nc2
amg_solve.c, 72	blas_smat.c, 105
fasp_amg_solve_nl_amli	fasp_blas_array_axpyz_nc3
amg_solve.c, 73	blas_smat.c, 106
fasp_array_cp	fasp_blas_array_axpyz_nc5
array.c, 78	blas_smat.c, 106
fasp_array_cp_nc3	fasp_blas_array_axpyz_nc7
array.c, 78	blas smat.c, 107
fasp_array_cp_nc5	fasp blas array dotprod
array.c, 79	blas_array.c, 84
fasp_array_cp_nc7	fasp_blas_array_norm1
array.c, 79	blas_array.c, 84
-	_ •
fasp_array_null	fasp_blas_array_norm2
array.c, 79	blas_array.c, 85
fasp_array_set	fasp_blas_array_norminf
array.c, 80	blas_array.c, 85
fasp_aux_bbyteToldouble	fasp_blas_bdbsr_aAxpy
convert.c, 136	blas_bcsr.c, 87
fasp_aux_change_endian4	fasp_blas_bdbsr_mxv
convert.c, 138	blas_bcsr.c, 88
fasp_aux_change_endian8	fasp_blas_bdcsr_aAxpy
convert.c, 138	blas_bcsr.c, 88
fasp_aux_dQuickSort	fasp_blas_bdcsr_mxv
ordering.c, 251	blas_bcsr.c, 88

fasp_blas_dbsr_aAxpby	fasp_blas_dvec_norminf
blas_bsr.c, 90	blas_vec.c, 126
fasp_blas_dbsr_aAxpy	fasp_blas_dvec_relerr
blas_bsr.c, 91	blas_vec.c, 126
fasp_blas_dbsr_mxv	fasp_blas_smat_aAxpby
blas_bsr.c, 91	blas_smat.c, 107
fasp_blas_dbsr_rap	fasp_blas_smat_inv
blas_bsr.c, 93	smat.c, 323
fasp_blas_dbsr_rap1	fasp_blas_smat_inv_nc2
blas_bsr.c, 93	smat.c, 323
fasp_blas_dcsr_aAxpy	fasp_blas_smat_inv_nc3
blas_csr.c, 95	smat.c, 323
fasp_blas_dcsr_aAxpy_agg	fasp_blas_smat_inv_nc4
blas_csr.c, 95	smat.c, 324
fasp_blas_dcsr_add	fasp_blas_smat_inv_nc5
blas_csr.c, 96	smat.c, 324
fasp_blas_dcsr_axm	fasp_blas_smat_inv_nc7
blas_csr.c, 96	smat.c, 324
fasp_blas_dcsr_mxm	fasp_blas_smat_mul
blas_csr.c, 97	blas_smat.c, 108
fasp_blas_dcsr_mxv	fasp_blas_smat_mul_nc2
blas_csr.c, 97	blas_smat.c, 108
fasp_blas_dcsr_mxv_agg	fasp_blas_smat_mul_nc3
blas_csr.c, 98	blas_smat.c, 109
fasp_blas_dcsr_ptap	fasp_blas_smat_mul_nc5
blas_csr.c, 98	blas_smat.c, 109
fasp_blas_dcsr_rap	fasp_blas_smat_mul_nc7
blas_csr.c, 99	blas_smat.c, 109
fasp_blas_dcsr_rap2	fasp_blas_smat_mxv
rap.c, 319	blas_smat.c, 110
fasp_blas_dcsr_rap4	fasp_blas_smat_mxv_nc2
blas_csr.c, 99	blas_smat.c, 110
fasp_blas_dcsr_rap_agg	fasp_blas_smat_mxv_nc3
blas_csr.c, 100 fasp_blas_dcsr_rap_agg1	blas_smat.c, 110
blas_csr.c, 100	fasp_blas_smat_mxv_nc5 blas_smat.c, 112
fasp_blas_dcsr_vmv	fasp_blas_smat_mxv_nc7
blas csr.c, 101	blas smat.c, 112
fasp_blas_dcsrl_mxv	fasp_blas_smat_ymAx
blas csrl.c, 102	blas_smat.c, 112
fasp_blas_dstr_aAxpy	fasp_blas_smat_ymAx_nc2
blas_str.c, 122	blas_smat.c, 114
fasp blas dstr mxv	fasp_blas_smat_ymAx_nc3
blas_str.c, 122	blas_smat.c, 114
fasp_blas_dvec_axpy	fasp_blas_smat_ymAx_nc5
blas_vec.c, 124	blas_smat.c, 115
fasp_blas_dvec_axpyz	fasp_blas_smat_ymAx_nc7
blas vec.c, 124	blas_smat.c, 115
fasp_blas_dvec_dotprod	fasp_blas_smat_ymAx_ns
blas_vec.c, 124	blas_smat.c, 116
fasp_blas_dvec_norm1	fasp_blas_smat_ymAx_ns2
blas_vec.c, 125	blas_smat.c, 116
fasp_blas_dvec_norm2	fasp_blas_smat_ymAx_ns3
blas_vec.c, 125	blas_smat.c, 117
5140_100.0, 1E0	5145_51114t.0, 1111

fasp_blas_smat_ymAx_ns5	sparse_bsr.c, 360
blas_smat.c, 117	fasp_dbsr_getblk
fasp_blas_smat_ymAx_ns7	sparse_block.c, 354
blas_smat.c, 118	fasp_dbsr_getblk_dcsr
fasp_blas_smat_ypAx	sparse_block.c, 354
blas_smat.c, 118	fasp_dbsr_getdiag
fasp_blas_smat_ypAx_nc2	sparse_bsr.c, 360
blas_smat.c, 119	fasp_dbsr_getdiaginv
fasp_blas_smat_ypAx_nc3	sparse_bsr.c, 361
blas_smat.c, 119	fasp_dbsr_null
fasp_blas_smat_ypAx_nc5	sparse_bsr.c, 361
blas_smat.c, 119	fasp_dbsr_plot
fasp_blas_smat_ypAx_nc7	graphics.c, 166
blas_smat.c, 121	fasp_dbsr_print
fasp_block.h, 151	io.c, 187
block_BSR, 152	fasp_dbsr_read
block_Reservoir, 152	io.c, 187
block_dCSRmat, 152	fasp_dbsr_trans
block_dvector, 152	sparse_bsr.c, 362
block iCSRmat, 152	fasp_dbsr_write
block_ivector, 152	io.c, 188
dBSRmat, 152	fasp_dbsr_write_coo
precond_block_reservoir_data, 153	io.c, 188
fasp_check_dCSRmat	fasp_dcoo1_read
checkmat.c, 128	io.c, 189
fasp_check_diagdom	fasp_dcoo_alloc
checkmat.c, 128	sparse_coo.c, 363
fasp_check_diagpos	fasp_dcoo_create
checkmat.c, 128	sparse coo.c, 363
fasp_check_diagzero	fasp_dcoo_free
checkmat.c, 130	sparse_coo.c, 363
fasp_check_iCSRmat	fasp_dcoo_print
checkmat.c, 130	io.c, 189
fasp_check_symm	fasp_dcoo_read
checkmat.c, 130	io.c, 189
fasp_chkerr	fasp_dcoo_shift
message.c, 228	sparse_coo.c, 364
fasp_dbsr_alloc	fasp_dcoo_write
sparse_bsr.c, 356	io.c, 190
fasp_dbsr_cp	fasp dcsr alloc
sparse_bsr.c, 357	sparse csr.c, 366
fasp_dbsr_create	fasp_dcsr_compress
sparse_bsr.c, 357	sparse_csr.c, 366
fasp dbsr diaginv	fasp_dcsr_compress_inplace
sparse_bsr.c, 358	
fasp_dbsr_diaginv2	sparse_csr.c, 366
• — — •	fasp_dcsr_cp
sparse_bsr.c, 358	sparse_csr.c, 367
fasp_dbsr_diaginv3	fasp_dcsr_create
sparse_bsr.c, 358	sparse_csr.c, 367
fasp_dbsr_diaginv4	fasp_dcsr_diagpref
sparse_bsr.c, 359	sparse_csr.c, 368
fasp_dbsr_diagpref	fasp_dcsr_eig
sparse_bsr.c, 359	eigen.c, 139
fasp_dbsr_free	fasp_dcsr_free

sparse_csr.c, 368	blas_str.c, 122
fasp_dcsr_getblk	fasp_dstr_free
sparse_block.c, 355	sparse_str.c, 381
fasp_dcsr_getcol	fasp_dstr_null
sparse_csr.c, 369	sparse_str.c, 381
fasp_dcsr_getdiag	fasp_dstr_print
sparse_csr.c, 369	io.c, 195
fasp_dcsr_multicoloring	fasp_dstr_read
sparse_csr.c, 369	io.c, 195
fasp_dcsr_null	fasp_dstr_write
sparse_csr.c, 371	io.c, 196
fasp_dcsr_perm	fasp_dvec_alloc
sparse_csr.c, 371	vec.c, 411
fasp_dcsr_print	fasp_dvec_cp
io.c, 190	vec.c, 411
fasp_dcsr_read	fasp_dvec_create
io.c, 191	vec.c, 411
fasp_dcsr_regdiag	fasp_dvec_free
sparse_csr.c, 372	vec.c, 412
fasp_dcsr_shift	fasp_dvec_isnan
sparse_csr.c, 372	vec.c, 412
fasp_dcsr_sort	fasp_dvec_maxdiff
sparse_csr.c, 372	vec.c, 412
fasp_dcsr_subplot	fasp_dvec_null
graphics.c, 167	vec.c, 413
fasp_dcsr_symdiagscale	fasp_dvec_print
sparse_csr.c, 374	io.c, 196
fasp_dcsr_sympat	fasp_dvec_rand
sparse_csr.c, 374	vec.c, 413
fasp_dcsr_trans	fasp_dvec_read
sparse_csr.c, 374	io.c, 196
fasp_dcsrl_create	fasp_dvec_set
sparse_csrl.c, 378	vec.c, 414
fasp_dcsrl_free	fasp_dvec_symdiagscale
sparse_csrl.c, 379	vec.c, 414
fasp_dcsrvec1_read	fasp_dvec_write
• — — —	io.c, 197
io.c, 191	
fasp_dcsrvec1_write io.c, 192	fasp_dvecind_read io.c, 197
fasp_dcsrvec2_read	fasp_dvecind_write
io.c, 192	io.c, 198
fasp_dcsrvec2_write	fasp_famg_solve
io.c, 193	amg_solve.c, 73
fasp_dmtx_read	fasp_format_bdcsr_dcsr
io.c, 194	formats.c, 154
fasp_dmtxsym_read	fasp_format_dbsr_dcoo
io.c, 194	formats.c, 155
fasp_dstr_alloc	fasp_format_dbsr_dcsr
sparse_str.c, 380	formats.c, 155
fasp_dstr_cp	fasp_format_dcoo_dcsr
sparse_str.c, 380	formats.c, 156
fasp_dstr_create	fasp_format_dcsr_dbsr
sparse_str.c, 381	formats.c, 156
fasp_dstr_diagscale	fasp_format_dcsr_dcoo

formats.c, 157	vec.c, 415
fasp_format_dcsrl_dcsr formats.c, 157	fasp_ivec_print
•	io.c, 198
fasp_format_dstr_dbsr	fasp_ivec_read
formats.c, 158	io.c, 199
fasp_format_dstr_dcsr	fasp_ivec_set
formats.c, 158	vec.c, 417
fasp_fwrapper_amg_	fasp_ivec_write
wrapper.c, 418	io.c, 199
fasp_fwrapper_krylov_amg_	fasp_ivecind_read
wrapper.c, 418	io.c, 200
fasp_gauss2d	fasp_matrix_read
quadrature.c, 318	io.c, 200
fasp_generate_diaginv_block	fasp_matrix_read_bin
smoother_str.c, 346	io.c, 201
fasp_gettime	fasp_matrix_write
timing.c, 409	io.c, 201
fasp_grid2d_plot	fasp_mem_check
graphics.c, 167	memory.c, 225
fasp_iarray_cp	fasp_mem_dcsr_check
array.c, 80	memory.c, 225
fasp_iarray_set	fasp_mem_free
array.c, 81	memory.c, 226
fasp_icsr_cp	fasp_mem_iludata_check
sparse_csr.c, 376	memory.c, 226
fasp_icsr_create	fasp_mem_realloc
sparse_csr.c, 376	memory.c, 227
fasp_icsr_free	fasp_mem_usage
sparse_csr.c, 377	memory.c, 227
fasp_icsr_null	fasp_param_amg_init
sparse_csr.c, 377	parameters.c, 257
fasp_icsr_trans	fasp_param_amg_print
sparse_csr.c, 377	parameters.c, 258
fasp_iden_free	fasp_param_amg_set
smat.c, 325	parameters.c, 258
fasp_ilu_data_alloc	fasp_param_amg_to_prec
init.c, 175	parameters.c, 258
fasp_ilu_data_free	fasp_param_amg_to_prec_bsr
init.c, 175	parameters.c, 259
fasp_ilu_data_null	fasp_param_ilu_init
init.c, 175	parameters.c, 259
fasp_ilu_dbsr_setup	fasp_param_ilu_print
ilu_setup_bsr.c, 169	parameters.c, 259
fasp_ilu_dcsr_setup	fasp_param_ilu_set
ilu_setup_csr.c, 170	parameters.c, 260
fasp_ilu_dstr_setup0	fasp_param_init
ilu_setup_str.c, 171	parameters.c, 260
fasp_ilu_dstr_setup1	fasp_param_input
ilu_setup_str.c, 172	input.c, 177
fasp_ivec_alloc	fasp_param_input_init
vec.c, 415	parameters.c, 261
fasp_ivec_create	fasp_param_prec_to_amg
vec.c, 415	parameters.c, 261
fasp_ivec_free	fasp_param_prec_to_amg_bsr

parameters.c, 261	precond_csr.c, 298
fasp_param_schwarz_init	fasp_precond_dstr_blockgs
parameters.c, 262	precond_str.c, 303
fasp_param_schwarz_print	fasp_precond_dstr_diag
parameters.c, 262	precond_str.c, 303
fasp_param_schwarz_set	fasp_precond_dstr_ilu0
parameters.c, 262	precond_str.c, 304
fasp_param_solver_init	fasp_precond_dstr_ilu0_backward
parameters.c, 263	precond_str.c, 304
fasp_param_solver_print	fasp_precond_dstr_ilu0_forward
parameters.c, 263	precond_str.c, 304
fasp_param_solver_set	fasp_precond_dstr_ilu1
parameters.c, 263	precond_str.c, 306
fasp_poisson_fgmg_1D	fasp_precond_dstr_ilu1_backward
gmg_poisson.c, 160	precond_str.c, 306 fasp_precond_dstr_ilu1_forward
fasp_poisson_fgmg_2D gmg_poisson.c, 161	precond_str.c, 306
fasp_poisson_fgmg_3D	fasp_precond_famg
gmg_poisson.c, 161	precond_csr.c, 298
fasp_poisson_gmg_1D	fasp_precond_free
gmg_poisson.c, 161	precond_csr.c, 299
fasp_poisson_gmg_2D	fasp_precond_ilu
gmg_poisson.c, 163	precond_csr.c, 299
fasp_poisson_gmg_3D	fasp_precond_ilu_backward
gmg_poisson.c, 163	precond_csr.c, 299
fasp_poisson_pcg_gmg_1D	fasp_precond_ilu_forward
gmg_poisson.c, 164	precond_csr.c, 300
fasp_poisson_pcg_gmg_2D	fasp_precond_nl_amli
gmg_poisson.c, 164	precond_csr.c, 300
fasp_poisson_pcg_gmg_3D	fasp_precond_null
gmg_poisson.c, 165	init.c, 176
fasp_precond_amg	fasp_precond_schwarz
precond_csr.c, 297	precond_csr.c, 300
fasp_precond_amli	fasp precond setup
precond_csr.c, 297	precond_csr.c, 302
fasp_precond_data_null	fasp_quad2d
parameters.c, 264	quadrature.c, 318
fasp_precond_dbsr_amg	fasp_schwarz_data_free
precond_bsr.c, 290	init.c, 176
fasp_precond_dbsr_diag	fasp_schwarz_setup
precond_bsr.c, 290	schwarz_setup.c, 321
fasp_precond_dbsr_diag_nc2	fasp_set_GS_threads
precond_bsr.c, 290	itsolver_bsr.c, 207
fasp_precond_dbsr_diag_nc3	fasp_smat_identity
precond_bsr.c, 292	smat.c, 325
fasp_precond_dbsr_diag_nc5	fasp_smat_identity_nc2
precond_bsr.c, 292	smat.c, 325
fasp_precond_dbsr_diag_nc7	fasp_smat_identity_nc3
precond_bsr.c, 294	smat.c, 327
fasp_precond_dbsr_ilu	fasp_smat_identity_nc5
precond_bsr.c, 294	smat.c, 327
fasp_precond_dbsr_nl_amli	fasp_smat_identity_nc7
precond_bsr.c, 296	smat.c, 327
fasp_precond_diag	fasp_smat_lu_decomp

lu.c, 223		smoother_csr.c, 341
fasp_smat_lu_solve	fasp_	_smoother_dcsr_sor_cf
lu.c, 224		smoother_csr.c, 342
fasp_smoother_dbsr_gs	fasp_	_smoother_dstr_gs
smoother_bsr.c, 329		smoother_str.c, 346
fasp smoother dbsr gs1	fasp	smoother_dstr_gs1
smoother_bsr.c, 329		smoother_str.c, 347
fasp_smoother_dbsr_gs_ascend		_smoother_dstr_gs_ascend
smoother_bsr.c, 330		smoother_str.c, 347
fasp_smoother_dbsr_gs_descend	fasp_	smoother_dstr_gs_cf
smoother_bsr.c, 330		smoother_str.c, 348
fasp_smoother_dbsr_gs_order1		_smoother_dstr_gs_descend
smoother_bsr.c, 331		smoother_str.c, 348
fasp_smoother_dbsr_gs_order2		_smoother_dstr_gs_order
smoother_bsr.c, 331		smoother_str.c, 349
fasp_smoother_dbsr_ilu		_smoother_dstr_jacobi
smoother_bsr.c, 332		smoother_str.c, 349
fasp_smoother_dbsr_jacobi		_smoother_dstr_jacobi1
smoother_bsr.c, 332		smoother_str.c, 350
fasp_smoother_dbsr_jacobi1		_smoother_dstr_schwarz
smoother bsr.c, 332		smoother_str.c, 350
fasp_smoother_dbsr_jacobi_setup		_smoother_dstr_sor
smoother_bsr.c, 334		smoother_str.c, 350
fasp smoother dbsr sor		_smoother_dstr_sor1
smoother_bsr.c, 334		smoother_str.c, 351
fasp_smoother_dbsr_sor1		_smoother_dstr_sor_ascend
smoother_bsr.c, 335		smoother_str.c, 351
fasp_smoother_dbsr_sor_ascend		_smoother_dstr_sor_cf
smoother_bsr.c, 335		smoother_str.c, 352
fasp_smoother_dbsr_sor_descend		_smoother_dstr_sor_descend
smoother_bsr.c, 336		smoother_str.c, 352
fasp_smoother_dbsr_sor_order		_smoother_dstr_sor_order
smoother_bsr.c, 336		smoother_str.c, 353
fasp_smoother_dcsr_L1diag	fasp	_solver_amg
smoother csr.c, 340		amg.c, 65
fasp_smoother_dcsr_gs		_solver_amli
smoother_csr.c, 338		amlirecur.c, 76
fasp_smoother_dcsr_gs_cf	fasp	solver bdcsr itsolver
smoother_csr.c, 338		itsolver_bcsr.c, 205
fasp_smoother_dcsr_gscr	fasp_	solver_bdcsr_krylov
smoother_csr_cr.c, 343		itsolver_bcsr.c, 205
fasp_smoother_dcsr_ilu	fasp_	_solver_bdcsr_pbcgs
smoother csr.c, 339		pbcgs.c, 266
fasp_smoother_dcsr_jacobi		_solver_bdcsr_pcg
smoother_csr.c, 339		pcg.c, 272
fasp_smoother_dcsr_kaczmarz		_solver_bdcsr_pgmres
smoother_csr.c, 340		pgmres.c, 279
fasp_smoother_dcsr_poly	fasp_	_solver_bdcsr_pminres
smoother_csr_poly.c, 344		pminres.c, 285
fasp_smoother_dcsr_poly_old		_solver_bdcsr_pvgmres
smoother_csr_poly.c, 344		pvgmres.c, 313
fasp_smoother_dcsr_sgs		_solver_bdcsr_spbcgs
smoother_csr.c, 341		spbcgs.c, 391
fasp_smoother_dcsr_sor		_solver_bdcsr_spcg

spcg.c, 396	pminres.c, 286
fasp_solver_bdcsr_spgmres	fasp_solver_dcsr_pvfgmres
spgmres.c, 399	pvfgmres.c, 310
fasp_solver_bdcsr_spminres	fasp_solver_dcsr_pvgmres
spminres.c, 403	pvgmres.c, 315
fasp_solver_bdcsr_spvgmres	fasp_solver_dcsr_spbcgs
spvgmres.c, 405	spbcgs.c, 392
fasp_solver_dbsr_itsolver	fasp_solver_dcsr_spcg
itsolver_bsr.c, 207	spcg.c, 397
fasp_solver_dbsr_krylov	fasp_solver_dcsr_spgmres
itsolver_bsr.c, 208	spgmres.c, 400
fasp_solver_dbsr_krylov_amg itsolver_bsr.c, 208	fasp_solver_dcsr_spminres spminres.c, 403
fasp_solver_dbsr_krylov_diag	fasp_solver_dcsr_spvgmres
itsolver_bsr.c, 209	spvgmres.c, 406
fasp solver dbsr krylov ilu	fasp_solver_dstr_itsolver
itsolver_bsr.c, 209	itsolver_str.c, 219
fasp_solver_dbsr_pbcgs	fasp_solver_dstr_krylov
pbcgs.c, 266	itsolver_str.c, 219
fasp_solver_dbsr_pgmres	fasp_solver_dstr_krylov_blockgs
pgmres.c, 279	itsolver_str.c, 220
fasp_solver_dbsr_pvfgmres	fasp_solver_dstr_krylov_diag
pvfgmres.c, 309	itsolver_str.c, 220
fasp_solver_dbsr_pvgmres	fasp_solver_dstr_krylov_ilu
pvgmres.c, 313	itsolver_str.c, 220
fasp_solver_dbsr_spbcgs	fasp_solver_dstr_pbcgs
spbcgs.c, 392	pbcgs.c, 268
fasp_solver_dbsr_spgmres	fasp_solver_dstr_pcg
spgmres.c, 399	pcg.c, 273
fasp_solver_dbsr_spvgmres	fasp_solver_dstr_pgmres
spvgmres.c, 406	pgmres.c, 282
fasp_solver_dcsr_itsolver	fasp_solver_dstr_pminres
itsolver_csr.c, 211	pminres.c, 286
fasp_solver_dcsr_krylov	fasp_solver_dstr_pvgmres
itsolver_csr.c, 212	pvgmres.c, 316
fasp_solver_dcsr_krylov_amg	fasp_solver_dstr_spbcgs
itsolver_csr.c, 212	spbcgs.c, 394
fasp_solver_dcsr_krylov_diag	fasp_solver_dstr_spcg
itsolver_csr.c, 213	spcg.c, 397
fasp_solver_dcsr_krylov_ilu	fasp_solver_dstr_spgmres
itsolver_csr.c, 213	spgmres.c, 400
fasp_solver_dcsr_krylov_ilu_M	fasp_solver_dstr_spminres
itsolver_csr.c, 214	spminres.c, 404
fasp_solver_dcsr_krylov_schwarz	fasp_solver_dstr_spvgmres
itsolver_csr.c, 214	spvgmres.c, 407
fasp_solver_dcsr_pbcgs	fasp_solver_famg
pbcgs.c, 267	famg.c, 141
	•
fasp_solver_dcsr_pcg	fasp_solver_fmgcycle
pcg.c, 272	fasp_solver_fmgcycle fmgcycle.c, 153
pcg.c, 272 fasp_solver_dcsr_pgcg	fasp_solver_fmgcycle fmgcycle.c, 153 fasp_solver_itsolver
pcg.c, 272 fasp_solver_dcsr_pgcg pgcg.c, 276	fasp_solver_fmgcycle fmgcycle.c, 153 fasp_solver_itsolver itsolver_mf.c, 216
pcg.c, 272 fasp_solver_dcsr_pgcg pgcg.c, 276 fasp_solver_dcsr_pgmres	fasp_solver_fmgcycle fmgcycle.c, 153 fasp_solver_itsolver itsolver_mf.c, 216 fasp_solver_itsolver_init
pcg.c, 272 fasp_solver_dcsr_pgcg pgcg.c, 276	fasp_solver_fmgcycle fmgcycle.c, 153 fasp_solver_itsolver itsolver_mf.c, 216

itsolver_mf.c, 217	sparse_util.c, 387
fasp_solver_mgcycle	fasp_sparse_ytx_
mgcycle.c, 248	sparse_util.c, 389
fasp_solver_mgcycle_bsr	fasp_sparse_ytxbig_
mgcycle.c, 248	sparse_util.c, 389
fasp_solver_mgrecur	fasp_vector_read
mgrecur.c, 249	io.c, 203
fasp_solver_mumps	fasp_vector_write
interface_mumps.c, 178	io.c, 204
fasp_solver_mumps_steps	fasp_wrapper_dbsr_krylov_amg
interface_mumps.c, 178	wrapper.c, 419
fasp_solver_nl_amli	fasp_wrapper_dcoo_dbsr_krylov_amg
amlirecur.c, 76	wrapper.c, 419
fasp_solver_nl_amli_bsr	fmgcycle.c, 153
amlirecur.c, 77	fasp_solver_fmgcycle, 153
fasp_solver_pbcgs	formats.c, 154
pbcgs_mf.c, 270	fasp_format_bdcsr_dcsr, 154
fasp_solver_pcg	fasp_format_dbsr_dcoo, 155
pcg_mf.c, 275	fasp_format_dbsr_dcsr, 155
fasp_solver_pgcg	fasp_format_dcoo_dcsr, 156
pgcg_mf.c, 277	fasp_format_dcsr_dbsr, 156
fasp_solver_pgmres	fasp_format_dcsr_dcoo, 157
pgmres_mf.c, 283	fasp_format_dcsrl_dcsr, 157
fasp_solver_pminres	fasp_format_dstr_dbsr, 158
pminres_mf.c, 288	fasp_format_dstr_dcsr, 158
fasp_solver_pvfgmres	
pvfgmres_mf.c, 311	GE
fasp_solver_pvgmres	fasp.h, 146
pvgmres_mf.c, 317	GT
fasp_solver_superlu	fasp.h, 146
interface_superlu.c, 180	givens.c, 159
fasp_solver_umfpack	fasp_aux_givens, 159
interface_umfpack.c, 181	gmg_poisson.c, 159
fasp_sparse_MIS	fasp_poisson_fgmg_1D, 160
sparse_util.c, 385	fasp_poisson_fgmg_2D, 161
fasp_sparse_aat_	fasp_poisson_fgmg_3D, 161
sparse_util.c, 383	fasp_poisson_gmg_1D, 161
fasp_sparse_abyb_	fasp_poisson_gmg_2D, 163
sparse_util.c, 383	fasp_poisson_gmg_3D, 163
fasp_sparse_abybms_	fasp_poisson_pcg_gmg_1D, 164
sparse_util.c, 384	fasp_poisson_pcg_gmg_2D, 164
fasp_sparse_aplbms_	fasp_poisson_pcg_gmg_3D, 165
sparse_util.c, 384	gmg_util.inl, 165
fasp_sparse_aplusb_	graphics.c, 166
sparse_util.c, 385	fasp_dbsr_plot, 166
fasp_sparse_iit_	fasp_dcsr_subplot, 167
sparse_util.c, 385	fasp_grid2d_plot, 167
fasp_sparse_rapcmp_	grid2d, 32
sparse_util.c, 386	e, 33
fasp_sparse_rapms_	edges, 33
	_
sparse_util.c, 386	ediri, 33
sparse_util.c, 386 fasp_sparse_wta_	_
. –	ediri, 33
fasp_sparse_wta_	ediri, 33 efather, 33

pdiri, 33	fasp_ilu_dstr_setup0, 171
pfather, 33	fasp_ilu_dstr_setup1, 172
s, 33	init.c, 172
t, 33	fasp_amg_data_bsr_create, 173
tfather, 34	fasp_amg_data_bsr_free, 173
triangles, 34	fasp_amg_data_create, 174
vertices, 34	fasp_amg_data_free, 174
	fasp_ilu_data_alloc, 175
iCOOmat, 34	fasp_ilu_data_free, 175
fasp.h, 149	fasp_ilu_data_null, 175
iCSRmat, 35	fasp_precond_null, 176
fasp.h, 149	fasp_schwarz_data_free, 176
ILU_data, 36	input.c, 176
ILU_droptol	fasp_param_input, 177
input_param, 42	input_param, 37
ILU Ifil	AMG_ILU_levels, 39
input_param, 42	AMG_aggressive_level, 39
ILU_param, 37	AMG_aggressive_path, 39
ILU_permtol	AMG_amli_degree, 39
input_param, 42	AMG_coarse_dof, 39
ILU relax	AMG_coarse_scaling, 39
input_param, 42	AMG_coarsening_type, 39
ILU_type	AMG_cycle_type, 39
input_param, 42	AMG_interpolation_type, 40
ILUk	AMG_levels, 40
messages.h, 238	AMG_max_aggregation, 40
ILUt	AMG_max_row_sum, 40
messages.h, 238	AMG_maxit, 40
ILUtp	AMG_nl_amli_krylov_type, 40
·	AMG_polynomial_degree, 40
messages.h, 239 IMAP	AMG_postsmooth_iter, 40
	AMG presmooth iter, 40
fasp.h, 150 INT	AMG_presmooth_iter, 40 AMG_relaxation, 41
	-
fasp.h, 146	AMG_schwarz_levels, 41
INTERP_DIR	AMG_smooth_filter, 41
messages.h, 239	AMG_smooth_order, 41
INTERP_ENG	AMG_smoother, 41
messages.h, 239	AMG_strong_coupled, 41
INTERP_STD	AMG_strong_threshold, 41
messages.h, 239	AMG_tentative_smooth, 41
ISNAN	AMG_tol, 41
fasp.h, 146	AMG_truncation_threshold, 42
ISPT	AMG_type, 42
messages.h, 239	ILU_droptol, 42
ISTART	ILU_lfil, 42
fasp.h, 146	ILU_permtol, 42
idenmat, 36	ILU_relax, 42
fasp.h, 149	ILU_type, 42
ilu.f, 168	itsolver_maxit, 42
ilu_setup_bsr.c, 168	itsolver_tol, 42
fasp_ilu_dbsr_setup, 169	output_type, 43
ilu_setup_csr.c, 170	precond_type, 43
fasp_ilu_dcsr_setup, 170	print_level, 43
ilu_setup_str.c, 171	problem_num, 43

restart, 43	fasp_matrix_write, 201
Schwarz_maxlvl, 43	fasp_vector_read, 203
Schwarz_mmsize, 43	fasp_vector_write, 204
Schwarz_type, 43	itsolver_bcsr.c, 205
solver_type, 43	fasp_solver_bdcsr_itsolver, 205
stop_type, 44	fasp_solver_bdcsr_krylov, 205
workdir, 44	itsolver_bsr.c, 206
interface_mumps.c, 177	fasp_set_GS_threads, 207
fasp_solver_mumps, 178	fasp_solver_dbsr_itsolver, 207
fasp_solver_mumps_steps, 178	fasp_solver_dbsr_krylov, 208
interface_samg.c, 179	fasp_solver_dbsr_krylov_amg, 208
dCSRmat2SAMGInput, 179	fasp_solver_dbsr_krylov_diag, 209
dvector2SAMGInput, 179	fasp_solver_dbsr_krylov_ilu, 209
interface_superlu.c, 180	THDs_AMG_GS, 210
fasp_solver_superlu, 180	THDs_CPR_gGS, 210
interface_umfpack.c, 181	THDs_CPR_IGS, 210
fasp_solver_umfpack, 181	itsolver_csr.c, 210
interpolation.c, 182	fasp_solver_dcsr_itsolver, 211
fasp_amg_interp, 182	fasp_solver_dcsr_krylov, 212
fasp_amg_interp1, 183	fasp_solver_dcsr_krylov_amg, 212
fasp_amg_interp_trunc, 183	fasp_solver_dcsr_krylov_diag, 213
interpolation_em.c, 184	fasp_solver_dcsr_krylov_ilu, 213
fasp_amg_interp_em, 184	fasp_solver_dcsr_krylov_ilu_M, 214
io.c, 185	fasp_solver_dcsr_krylov_schwarz, 214
fasp_dbsr_print, 187	itsolver_maxit
fasp_dbsr_read, 187	input_param, 42
fasp_dbsr_write, 188	itsolver_mf.c, 215
fasp_dbsr_write_coo, 188	fasp_solver_itsolver, 216
fasp_dcoo1_read, 189	fasp_solver_itsolver_init, 217
fasp_dcoo_print, 189	fasp_solver_krylov, 217
fasp_dcoo_read, 189	itsolver_param, 44
fasp_dcoo_write, 190	itsolver_type, 44
fasp_dcsr_print, 190	maxit, 44
fasp_dcsr_read, 191	precond_type, 45
fasp_dcsrvec1_read, 191	print_level, 45
fasp dcsrvec1 write, 192	restart, 45
fasp_dcsrvec2_read, 192	stop_type, 45
fasp dcsrvec2 write, 193	tol, 45
fasp_dmtx_read, 194	itsolver_str.c, 218
fasp_dmtxsym_read, 194	fasp solver dstr itsolver, 219
fasp dstr print, 195	fasp solver dstr krylov, 219
fasp_dstr_read, 195	fasp_solver_dstr_krylov_blockgs, 220
fasp_dstr_read, 135	fasp_solver_dstr_krylov_diag, 220
fasp_dvec_print, 196	fasp_solver_dstr_krylov_ilu, 220
fasp_dvec_read, 196	itsolver tol
fasp_dvec_write, 197	_
• — —	input_param, 42
fasp_dvecind_read, 197	itsolver_type
fasp_dvecind_write, 198	itsolver_param, 44
fasp_ivec_print, 198	itsolver_util.inl, 221
fasp_ivec_read, 199	ivector, 45
fasp_ivec_write, 199	fasp.h, 149
fasp_ivecind_read, 200	14
fasp_matrix_read, 200	JA
fasp_matrix_read_bin, 201	dBSRmat, 27

LE	fasp.h, 147
fasp.h, 146	maxit
LIST_HEAD	itsolver_param, 44
linklist.inl, 222	precond_FASP_blkoil_data, 60
LIST_TAIL	memory.c, 224
linklist.inl, 222	fasp_mem_check, 225
LONG	fasp_mem_dcsr_check, 225
fasp.h, 146	fasp_mem_free, 226
LONGLONG	fasp mem iludata check, 226
fasp.h, 146	fasp_mem_realloc, 227
LS	fasp_mem_usage, 227
fasp.h, 147	total_alloc_count, 227
Link, 46	total_alloc_mem, 227
LinkList	message.c, 228
	_
fasp.h, 149	fasp_chkerr, 228
linked_list, 46	print_amgcomplexity, 229
linklist.inl, 222	print_amgcomplexity_bsr, 229
LIST_HEAD, 222	print_cputime, 229
LIST_TAIL, 222	print_itinfo, 230
ListElement	print_message, 230
fasp.h, 150	messages.h, 231
lu.c, 223	AMLI_CYCLE, 234
fasp_smat_lu_decomp, 223	ASCEND, 234
fasp_smat_lu_solve, 224	CF_ORDER, 234
	CGPT, 234
MAT_BSR	CLASSIC_AMG, 234
messages.h, 239	COARSE_AC, 234
MAT_CSR	COARSE_CR, 234
messages.h, 240	COARSE_RS, 235
MAT_CSRL	CPFIRST, 235
messages.h, 240	DESCEND, 235
MAT_FREE	ERROR_ALLOC_MEM, 235
messages.h, 240	ERROR_AMG_COARSEING, 235
MAT_STR	ERROR_DATA_ZERODIAG, 236
messages.h, 240	ERROR_DUMMY_VAR, 236
MAT_SymCSR	ERROR INPUT PAR, 236
messages.h, 240	ERROR_MISC, 236
MAT bBSR	ERROR NUM BLOCKS, 236
messages.h, 239	ERROR OPEN FILE, 236
MAT bCSR	ERROR QUAD DIM, 236
messages.h, 239	ERROR_QUAD_TYPE, 237
MAX	ERROR REGRESS, 237
fasp.h, 147	ERROR SOLVER EXIT, 237
MAX AMG LVL	ERROR SOLVER MAXIT, 237
fasp.h, 147	ERROR_SOLVER_MISC, 237
MAX REFINE LVL	ERROR_SOLVER_STAG, 237
fasp.h, 147	ERROR SOLVER TYPE, 238
MAX RESTART	ERROR WRONG FILE, 238
fasp.h, 147	FALSE, 238
MAX STAG	FGPT, 238
_	
fasp.h, 147	FPFIRST, 238
MAXIMAP	ILUk, 238
fasp.h, 150	ILUt, 238
MIN	ILUtp, 239

INTERP DIR, 239	SOLVER SUPERLU, 245
INTERP ENG, 239	SOLVER SVFGMRES, 246
INTERP STD, 239	SOLVER SVGMRES, 246
ISPT, 239	SOLVER UMFPACK, 246
MAT BSR, 239	SOLVER VFGMRES, 246
MAT CSR, 240	SOLVER VGMRES, 246
MAT CSRL, 240	STOP MOD REL RES, 246
MAT FREE, 240	STOP REL PRECRES, 246
MAT_STR, 240	STOP REL RES, 246
MAT_SymCSR, 240	SUCCESS, 246
MAT bBSR, 239	TRUE, 247
MAT bCSR, 239	UA AMG, 247
NL AMLI CYCLE, 240	UNPT, 247
NO ORDER, 240	USERDEFINED, 247
OFF, 240	V CYCLE, 247
ON, 241	W CYCLE, 247
PREC AMG, 241	mg_util.inl, 247
PREC DIAG, 241	mgcycle.c, 248
PREC_FMG, 241	fasp_solver_mgcycle, 248
PREC ILU, 241	fasp_solver_mgcycle_bsr, 248
PREC NULL, 241	mgl data
PREC_SCHWARZ, 241	precond_FASP_blkoil_data, 60
PRINT_ALL, 241	mgrecur.c, 249
	fasp_solver_mgrecur, 249
PRINT_MIN, 242	mxv_matfree, 47
PRINT_MORE, 242	
PRINT_MOST, 242	N2C
PRINT_NONE, 242	fasp.h, 147
PRINT_SOME, 242	NEDMALLOC
RUN_FAIL, 242	fasp.h, 148
SA_AMG, 242	NL_AMLI_CYCLE
SMOOTHER_BLKOIL, 242	messages.h, 240
SMOOTHER_CG, 243	NO_ORDER
SMOOTHER_GS, 243	messages.h, 240
SMOOTHER_GSOR, 243	neigh
SMOOTHER_JACOBI, 243	precond_FASP_blkoil_data, 60
SMOOTHER_L1DIAG, 243	nx_rb
SMOOTHER_POLY, 243	fasp.h, 150
SMOOTHER_SGS, 243	ny_rb
SMOOTHER_SGSOR, 243	fasp.h, 150
SMOOTHER_SOR, 244	nz_rb
SMOOTHER_SSOR, 244	fasp.h, 150
SOLVER_AMG, 244	
SOLVER_BiCGstab, 244	OFF
SOLVER_CG, 244	messages.h, 240
SOLVER_FMG, 244	ON
SOLVER_GCG, 244	messages.h, 241
SOLVER_GMRES, 244	OPENMP_HOLDS
SOLVER_MUMPS, 245	fasp.h, 148
SOLVER_MinRes, 245	order
SOLVER_SBiCGstab, 245	precond_block_reservoir_data, 51
SOLVER_SCG, 245	precond_FASP_blkoil_data, 60
SOLVER_SGCG, 245	ordering.c, 250
SOLVER_SGMRES, 245	fasp_BinarySearch, 255
SOLVER_SMinRes, 245	fasp_aux_dQuickSort, 251

fasp_aux_dQuickSortIndex, 252	fasp_param_solver_init, 263
fasp_aux_iQuickSort, 252	fasp_param_solver_print, 263
fasp_aux_iQuickSortIndex, 253	fasp_param_solver_set, 263
fasp_aux_merge, 253	fasp_precond_data_null, 264
fasp_aux_msort, 254	pbcgs.c, 264
fasp_aux_unique, 254	fasp_solver_bdcsr_pbcgs, 266
output_type	fasp_solver_dbsr_pbcgs, 266
input_param, 43	fasp solver dcsr pbcgs, 267
F	fasp_solver_dstr_pbcgs, 268
p	pbcgs_mf.c, 268
grid2d, 33	fasp_solver_pbcgs, 270
PP	pcg.c, 270
precond_block_reservoir_data, 51	fasp_solver_bdcsr_pcg, 272
precond_FASP_blkoil_data, 61	fasp_solver_dcsr_pcg, 272
PREC AMG	
-	fasp_solver_dstr_pcg, 273
messages.h, 241	pcg_mf.c, 274
PREC_DIAG	fasp_solver_pcg, 275
messages.h, 241	pcgrid2d
PREC_FMG	fasp.h, 150
messages.h, 241	pdiri
PREC_ILU	grid2d, 33
messages.h, 241	perf_idx
PREC_NULL	precond_block_reservoir_data, 51
messages.h, 241	precond_FASP_blkoil_data, 60
PREC_SCHWARZ	perf_neigh
messages.h, 241	precond_FASP_blkoil_data, 60
PRINT_ALL	pfather
messages.h, 241	grid2d, <mark>33</mark>
PRINT_MIN	pgcg.c, 276
messages.h, 242	fasp_solver_dcsr_pgcg, 276
PRINT MORE	pgcg_mf.c, 277
messages.h, 242	fasp_solver_pgcg, 277
PRINT MOST	pgmres.c, 278
messages.h, 242	fasp_solver_bdcsr_pgmres, 279
PRINT NONE	fasp_solver_dbsr_pgmres, 279
messages.h, 242	fasp_solver_dcsr_pgmres, 281
PRINT_SOME	fasp_solver_dstr_pgmres, 282
messages.h, 242	pgmres_mf.c, 282
parameters.c, 255	fasp solver pgmres, 283
fasp param amg init, 257	pgrid2d
fasp_param_amg_print, 258	fasp.h, 150
· — — — —	•
fasp_param_amg_set, 258	pivot
fasp_param_amg_to_prec, 258	precond_block_reservoir_data, 51
fasp_param_amg_to_prec_bsr, 259	precond_FASP_blkoil_data, 60
fasp_param_ilu_init, 259	pivot_S
fasp_param_ilu_print, 259	precond_FASP_blkoil_data, 61
fasp_param_ilu_set, 260	pivotS
fasp_param_init, 260	precond_block_reservoir_data, 51
fasp_param_input_init, 261	pminres.c, 284
fasp_param_prec_to_amg, 261	fasp_solver_bdcsr_pminres, 285
fasp_param_prec_to_amg_bsr, 261	fasp_solver_dcsr_pminres, 286
fasp_param_schwarz_init, 262	fasp_solver_dstr_pminres, 286
fasp_param_schwarz_print, 262	pminres_mf.c, 287
fasp_param_schwarz_set, 262	fasp_solver_pminres, 288

precond, 47	fasp_precond_dbsr_ilu, 294
precond_FASP_blkoil_data, 58	fasp_precond_dbsr_nl_amli, 296
A, 59	precond_csr.c, 296
diaginv, 59	fasp_precond_amg, 297
diaginv_S, 60	fasp_precond_amli, 297
diaginv_noscale, 60	fasp_precond_diag, 298
maxit, 60	fasp_precond_famg, 298
mgl_data, 60	fasp_precond_free, 299
neigh, 60	fasp_precond_ilu, 299
order, 60	fasp_precond_ilu_backward, 299
PP, 61	fasp_precond_ilu_forward, 300
perf_idx, 60	fasp_precond_nl_amli, 300
perf_neigh, 60	fasp_precond_schwarz, 300
pivot, 60	fasp_precond_setup, 302
pivot_S, 61	precond_data, 52
r, 61	precond_data_bsr, 54
RR, 61	precond_data_str, 55
	• — —
restart, 61 SS, 61	precond_diagetr, 57
•	precond_diagstr, 57
scaled, 61	precond_str.c, 302
tol, 61	fasp_precond_dstr_blockgs, 303
w, 62	fasp_precond_dstr_diag, 303
WW, 62	fasp_precond_dstr_ilu0, 304
precond_block_data, 48	fasp_precond_dstr_ilu0_backward, 304
A, 48	fasp_precond_dstr_ilu0_forward, 304
Aarray, 48	fasp_precond_dstr_ilu1, 306
Ablock, 48	fasp_precond_dstr_ilu1_backward, 306
amgparam, 49	fasp_precond_dstr_ilu1_forward, 306
col_idx, 49	precond_type
r, 49	input_param, 43
row_idx, 49	itsolver_param, 45
precond_block_reservoir_data, 49	print_amgcomplexity
diag, 51	message.c, 229
diaginv, 51	print_amgcomplexity_bsr
diaginvS, 51	message.c, 229
fasp_block.h, 153	print_cputime
order, 51	message.c, 229
PP, 51	print_itinfo
perf_idx, 51	message.c, 230
pivot, 51	print level
pivotS, 51	input_param, 43
r, 52	itsolver_param, 45
RR, 52	print_message
SS, 52	message.c, 230
scaled, 52	problem num
w, 52	input_param, 43
WW, 52	pvfgmres.c, 308
precond_bsr.c, 289	fasp_solver_dbsr_pvfgmres, 309
fasp_precond_dbsr_amg, 290	fasp_solver_dcsr_pvfgmres, 310
fasp_precond_dbsr_diag, 290	pvfgmres_mf.c, 311
fasp_precond_dbsr_diag_nc2, 290	fasp_solver_pvfgmres, 311
fasp_precond_dbsr_diag_nc3, 292	pvgmres.c, 312
fasp_precond_dbsr_diag_nc5, 292	fasp_solver_bdcsr_pvgmres, 313
fasp_precond_dbsr_diag_nc7, 294	fasp_solver_dbsr_pvgmres, 313
iasp_pieconiu_uosi_uiay_nc/, 234	iasp_solvei_absi_pvgiiiies, 313

fasp_solver_dcsr_pvgmres, 315	SMOOTHER_SGSOR
fasp_solver_dstr_pvgmres, 316	messages.h, 243
pvgmres_mf.c, 316	SMOOTHER SOR
fasp_solver_pvgmres, 317	messages.h, 244
lasp_solver_pvgmles, 517	
quadrature.c, 318	SMOOTHER_SSOR
•	messages.h, 244
fasp_gauss2d, 318	SOLVER_AMG
fasp_quad2d, 318	messages.h, 244
	SOLVER_BiCGstab
r	messages.h, 244
precond_block_data, 49	SOLVER CG
precond_block_reservoir_data, 52	messages.h, 244
precond_FASP_blkoil_data, 61	SOLVER_FMG
REAL	
fasp.h, 148	messages.h, 244
RR	SOLVER_GCG
precond block reservoir data, 52	messages.h, 244
precond FASP blkoil data, 61	SOLVER_GMRES
. – – –	messages.h, 244
RS_C1	SOLVER MUMPS
fasp.h, 148	messages.h, 245
RUN_FAIL	SOLVER MinRes
messages.h, 242	messages.h, 245
rap.c, 319	-
fasp_blas_dcsr_rap2, 319	SOLVER_SBiCGstab
restart	messages.h, 245
input_param, 43	SOLVER_SCG
itsolver_param, 45	messages.h, 245
precond_FASP_blkoil_data, 61	SOLVER_SGCG
• – – –	messages.h, 245
row_idx	SOLVER SGMRES
precond_block_data, 49	messages.h, 245
	SOLVER_SMinRes
S suidod co	messages.h, 245
grid2d, 33	SOLVER SUPERLU
SA_AMG	-
messages.h, 242	messages.h, 245
SHORT	SOLVER_SVFGMRES
fasp.h, 148	messages.h, 246
SMALLREAL	SOLVER_SVGMRES
fasp.h, 148	messages.h, 246
SMOOTHER BLKOIL	SOLVER_UMFPACK
messages.h, 242	messages.h, 246
SMOOTHER CG	SOLVER_VFGMRES
messages.h, 243	messages.h, 246
SMOOTHER_GS	SOLVER VGMRES
	messages.h, 246
messages.h, 243	
SMOOTHER_GSOR	SS
messages.h, 243	precond_block_reservoir_data, 52
SMOOTHER_JACOBI	precond_FASP_blkoil_data, 61
messages.h, 243	STAG_RATIO
SMOOTHER_L1DIAG	fasp.h, 148
messages.h, 243	STOP_MOD_REL_RES
SMOOTHER_POLY	messages.h, 246
messages.h, 243	STOP REL PRECRES
SMOOTHER_SGS	messages.h, 246
messages.h, 243	STOP REL RES
ποσσαμοσ.π, 270	OTOT_TILL_TILD

messages.h, 246	fasp_smoother_dcsr_sor, 341
SUCCESS	fasp_smoother_dcsr_sor_cf, 342
messages.h, 246	smoother_csr_cr.c, 342
scaled	fasp_smoother_dcsr_gscr, 343
precond_block_reservoir_data, 52	smoother_csr_poly.c, 344
precond FASP blkoil data, 61	fasp_smoother_dcsr_poly, 344
schwarz.f, 320	fasp_smoother_dcsr_poly_old, 344
Schwarz_data, 62	smoother_str.c, 345
Schwarz_maxlvl	fasp_generate_diaginv_block, 346
input_param, 43	fasp_smoother_dstr_gs, 346
Schwarz_mmsize	fasp smoother dstr gs1, 347
input_param, 43	fasp_smoother_dstr_gs_ascend, 347
Schwarz_param, 63	fasp_smoother_dstr_gs_cf, 348
schwarz_setup.c, 321	fasp_smoother_dstr_gs_descend, 348
fasp_schwarz_setup, 321	fasp_smoother_dstr_gs_order, 349
	fasp_smoother_dstr_jacobi, 349
Schwarz_type	fasp smoother dstr jacobi1, 350
input_param, 43	
smat.c, 322	fasp_smoother_dstr_schwarz, 350
fasp_blas_smat_inv, 323	fasp_smoother_dstr_sor, 350
fasp_blas_smat_inv_nc2, 323	fasp_smoother_dstr_sor1, 351
fasp_blas_smat_inv_nc3, 323	fasp_smoother_dstr_sor_ascend, 351
fasp_blas_smat_inv_nc4, 324	fasp_smoother_dstr_sor_cf, 352
fasp_blas_smat_inv_nc5, 324	fasp_smoother_dstr_sor_descend, 352
fasp_blas_smat_inv_nc7, 324	fasp_smoother_dstr_sor_order, 353
fasp_iden_free, 325	solver_type
fasp_smat_identity, 325	input_param, 43
fasp_smat_identity_nc2, 325	sparse_block.c, 353
fasp_smat_identity_nc3, 327	fasp_dbsr_getblk, 354
fasp_smat_identity_nc5, 327	fasp_dbsr_getblk_dcsr, 354
fasp_smat_identity_nc7, 327	fasp_dcsr_getblk, 355
smoother_bsr.c, 328	sparse_bsr.c, 355
fasp_smoother_dbsr_gs, 329	fasp_dbsr_alloc, 356
fasp_smoother_dbsr_gs1, 329	fasp_dbsr_cp, 357
fasp_smoother_dbsr_gs_ascend, 330	fasp dbsr create, 357
fasp_smoother_dbsr_gs_descend, 330	fasp_dbsr_diaginv, 358
fasp smoother dbsr gs order1, 331	fasp_dbsr_diaginv2, 358
fasp_smoother_dbsr_gs_order2, 331	fasp dbsr diaginv3, 358
fasp_smoother_dbsr_ilu, 332	fasp_dbsr_diaginv4, 359
fasp smoother dbsr jacobi, 332	fasp dbsr diagpref, 359
fasp_smoother_dbsr_jacobi1, 332	fasp_dbsr_free, 360
fasp smoother dbsr jacobi setup, 334	fasp_dbsr_getdiag, 360
fasp_smoother_dbsr_sor, 334	fasp_dbsr_getdiaginv, 361
fasp smoother dbsr sor1, 335	fasp dbsr null, 361
fasp smoother dbsr sor ascend, 335	fasp_dbsr_trans, 362
fasp_smoother_dbsr_sor_descend, 336	sparse_coo.c, 362
fasp_smoother_dbsr_sor_order, 336	fasp_dcoo_alloc, 363
smoother_csr.c, 337	• — —
	fasp_dcoo_create, 363
fasp_smoother_dcsr_L1diag, 340	fasp_dcoo_free, 363
fasp_smoother_dcsr_gs, 338	fasp_dcoo_shift, 364
fasp_smoother_dcsr_gs_cf, 338	sparse_csr.c, 364
fasp_smoother_dcsr_ilu, 339	fasp_dcsr_alloc, 366
fasp_smoother_dcsr_jacobi, 339	fasp_dcsr_compress, 366
fasp_smoother_dcsr_kaczmarz, 340	fasp_dcsr_compress_inplace, 366
fasp_smoother_dcsr_sgs, 341	fasp_dcsr_cp, 367

fasp_dcsr_create, 367	fasp_solver_dcsr_spgmres, 400
fasp_dcsr_diagpref, 368	fasp_solver_dstr_spgmres, 400
fasp_dcsr_free, 368	spminres.c, 401
fasp_dcsr_getcol, 369	fasp_solver_bdcsr_spminres, 403
fasp_dcsr_getdiag, 369	fasp_solver_dcsr_spminres, 403
fasp_dcsr_multicoloring, 369	fasp_solver_dstr_spminres, 404
fasp_dcsr_null, 371	spvgmres.c, 405
fasp_dcsr_perm, 371	fasp_solver_bdcsr_spvgmres, 405
fasp_dcsr_regdiag, 372	fasp_solver_dbsr_spvgmres, 406
fasp_dcsr_shift, 372	fasp_solver_dcsr_spvgmres, 406
fasp_dcsr_sort, 372	fasp_solver_dstr_spvgmres, 407
fasp_dcsr_symdiagscale, 374	stop_type
fasp_dcsr_sympat, 374	input_param, 44
fasp_dcsr_trans, 374	itsolver_param, 45
fasp_icsr_cp, 376	
fasp_icsr_create, 376	t
fasp_icsr_free, 377	grid2d, 33
fasp_icsr_null, 377	THDs_AMG_GS
fasp_icsr_trans, 377	itsolver_bsr.c, 210
sparse_csrl.c, 378	THDs_CPR_gGS
fasp dcsrl create, 378	itsolver_bsr.c, 210
fasp_dcsrl_free, 379	THDs_CPR_IGS
sparse_str.c, 379	itsolver_bsr.c, 210
fasp_dstr_alloc, 380	TRUE
fasp_dstr_cp, 380	messages.h, 247
fasp_dstr_create, 381	tfather
fasp_dstr_free, 381	grid2d, 34
fasp_dstr_null, 381	threads.c, 408
sparse_util.c, 382	FASP_GET_START_END, 408
fasp_sparse_MIS, 385	timing.c, 409
fasp_sparse_aat_, 383	fasp_gettime, 409
fasp_sparse_abyb_, 383	tol
fasp_sparse_abybms_, 384	itsolver_param, 45
fasp sparse aplbms , 384	precond_FASP_blkoil_data, 61
	total_alloc_count
fasp_sparse_aplusb_, 385	fasp.h, 150
fasp_sparse_iit_, 385	memory.c, 227
fasp_sparse_rapcmp_, 386	total_alloc_mem
fasp_sparse_rapms_, 386	fasp.h, 150
fasp_sparse_wta_, 387	memory.c, 227
fasp_sparse_wtams_, 387	triangles
fasp_sparse_ytx_, 389	grid2d, 34
fasp_sparse_ytxbig_, 389	
spbcgs.c, 390	UA_AMG
fasp_solver_bdcsr_spbcgs, 391	messages.h, 247
fasp_solver_dbsr_spbcgs, 392	UNPT
fasp_solver_dcsr_spbcgs, 392	messages.h, 247
fasp_solver_dstr_spbcgs, 394	USERDEFINED
spcg.c, 395	messages.h, 247
fasp_solver_bdcsr_spcg, 396	-
fasp_solver_dcsr_spcg, 397	V_CYCLE
fasp_solver_dstr_spcg, 397	messages.h, 247
spgmres.c, 398	val
fasp_solver_bdcsr_spgmres, 399	dBSRmat, 27
fasp_solver_dbsr_spgmres, 399	vec.c, 410

```
fasp_dvec_alloc, 411
    fasp_dvec_cp, 411
    fasp_dvec_create, 411
    fasp_dvec_free, 412
    fasp_dvec_isnan, 412
    fasp_dvec_maxdiff, 412
    fasp dvec null, 413
    fasp_dvec_rand, 413
    fasp dvec set, 414
    fasp_dvec_symdiagscale, 414
    fasp_ivec_alloc, 415
    fasp_ivec_create, 415
    fasp ivec free, 415
    fasp_ivec_set, 417
vertices
    grid2d, 34
W
    precond_block_reservoir_data, 52
    precond_FASP_blkoil_data, 62
W_CYCLE
    messages.h, 247
ww
    precond_block_reservoir_data, 52
    precond_FASP_blkoil_data, 62
workdir
    input_param, 44
wrapper.c, 417
    fasp_fwrapper_amg_, 418
    fasp_fwrapper_krylov_amg_, 418
    fasp_wrapper_dbsr_krylov_amg, 419
    fasp_wrapper_dcoo_dbsr_krylov_amg, 419
```