




Operational Best Practices

ACE Team

CoPilot Remote Syslog

- The Syslog server is by default the CoPilot.
 - □ When you deploy the CoPilot, automatically the Controller will open the port UDP **5000** (Syslog) on the Security Group attached to the CoPilot instance.
 - Aviatrix CoPilot Remote Syslog Profile is set to use the Profile 9.





In the **CoPilot > Settings > Configuration > Logging Services** page, you can configure the forwarding of logs from the Aviatrix platform to the log servers of well known log management systems.

Profile 2			×
Profile Name			
SolarWind	s' Kiwi S	yslog	
Server			
57 U			
rotocol		Port	
UDP	~	5000	
Certifi	cate		
Custor	n Temp	ate	
	ced Sett		




CoPilot NetFlow

AVIATRIX
ACE

AVIATRIX CERTIFIED
ENGINEER

- The NetFlow collector is by default the CoPilot.
 - □ When you deploy the CoPilot, automatically the Controller will open the port UDP **31283** (NetFlow) on the Security Group attached to the CoPilot instance.
 - □ All the Aviatrix Gateways will send NetFlow data to the CoPilot.
 - □ As a consequence, FlowIQ feature in Aviatrix CoPilot will start to process the NetFlow information received by the Gateways.



In the CoPilot > Settings > Configuration >
 Logging Services page, you can configure
 the forwarding of the NetFlow Data from the
 Aviatrix platform to your designated service
 point.

Manage Netflow Agent						
Repository						
Server						


Port	Version					
31283	9		~			
Mode						
O IPT						
Compare the previous Preview Feature						
 Advanced Settings 						
Disable		Cancel	Save			



CoPilot Alerts Configuration



- Webhooks Integrations work with any 3rd party integration (Slack, PagerDuty, ServiceNow, etc.)
- 2. Add webhook endpoints (can send payload as JSON or text)
- 3. Provide custom tags in the payload to classify triggered events and further integrate into your systems
- 4. Get alerted via webhook and email for the same alert








Role-Based Access Control (RBAC)



RBAC: Role-Based Access Control



Aviatrix RBAC is based on the "Users" and "Permission Group" concept









User Access- CoPilot






Permission Group (part.1)




ACE



Permission Group (part.2)







Authentication Phase

AVIATRIX
ACE
AVIATRIX CERTIFIED
ENGINEER

- Users can be authenticated:
 - Locally on the Aviatrix Controller
 - Onboard Users (Admin, Operators, Developers, Read-Only)
 - Allowed to reset their password
 - Using SAML IDP
 - Onboard Users (Admin, Operators, Developers, Read-Only)
 - Other functionality depends on IDP





















SAML Integration Example – Identity Provider

RBAC User: developer

RBAC User: Admin

Account-Admin

Super-Users

read_only


RBAC User: Account A-B


RBAC User: SecOps

Account Admins (A&B)

Account Admins (C&D)

Security-Users








okta

ACE





Admin/Super-Users Admin



Account Admins
Account-A&B



Security-User SecOps



Developers/Read Only Developer




Configuring SAML Authentication



User can be authenticated using the local database or using the SAML Integration.

Go to CoPilot > Administration > User Access > Access Management



Create SAML Endpoint

SAML Endpoint Configuration

Name

Octa



Aviatrix Controller High Availability (HA)



Aviatrix Controller High Availability (HA)




- Very important: <u>Controller is not in the data path</u>
- If Controller is down → Data Plane still functions
- Your cloud network is still up and running
- Do not compare on-prem to cloud
 - Hardware devices cannot be replaced / software is more flexible
 - Cloud operating models are different
 - Cloud processes are different
 - We need a fresh and different look to solve



Aviatrix Controller HA Process



- Takes minutes to switch over to new controller
 - Depends on factors such as AWS latency, instance type, size of the DB, etc.
- Previous controller is terminated
- All existing configuration is restored
- New Private IP is assigned (new AZ)
- New controller stays at the same version as previous




https://docs.aviatrix.com/HowTos/controller_ha.html
https://github.com/AviatrixSystems/Controller-HA-for-AWS/



Aviatrix Controller HA Process



- Aviatrix Controller HA operates by relying on an AWS Auto Scaling Group
- The Auto Scaling Group has a desired capacity of 1
- If the Controller EC2 instance is stopped or terminated, it will be automatically re-deployed by the Auto Scaling Group
- An AWS Lambda script is notified via SNS when new instances are launched by the Auto Scaling Group
- This script handles configuration restore using the most recent Controller backup file, stored in S3





Securing Aviatrix Controller with Application Load Balancer




Applies to any cloud

AVIATRIX
ACE

AVIATRIX CERTIFIED
ENGINEER


- Confirm that the Controller Security Group
 Management is NOT disabled to only allow access
 to the Controller EIP from
 Aviatrix Gateways
- Create a new internet facing ALB
- Modify main Controller Security
 Group to only allow access from the ALB Security Group
- Enable WAF on the ALB with AWS Managed Rules
- Adjust ALB idle timeout, modify rulesets
- Modify ALB Security Group to only allow access from the admin user IP



Azure



- Use WAF with Azure Managed rules on Application Gateway to limit usual web hacks/attacks against Controller
- Only allow user access from the Application Gateway subnet to Controller on port 443 (Controller Security Groups management feature is a pre-requisite for gateway communication to Controller)
- Allow configuring user access on non-standard HTTPS listener port
- Terminate SSL connection on Application Gateway to leverage cloud native certificate management and WAF capability to inspect and log requests
- L7 health-check on the Controller





Gateway and Controller Sizing



Controller Sizing



Controller uses multiple cores to handle the API query load generated by CoPilot →
Minimum 4 core instance

- Resizing:
 - If you do not use User VPN
 - Stopping the controller to resize does not impact the data traffic
 - □ Always good practice to backup controller before performing upgrade
 - If you use User VPN
 - □ No impact to connected users, but new connections could not be established during the stop and resize
- Maintenance Windows for resizing usually do not require more than 15 minutes

Gateway Sizing



- Gateway selection affects expected throughput
- If you decide to enable High Performance Encryption
 - Use Jumbo MTU and to verify MTU along the path
 - Go to TROUBLESHOOT > Diagnostics > Network
 - Select a gateway and destination IP address, click Trace Path
 - It will display MTU of the devices along the path

Secure Egress

- T2.micro is not adequate, for instance
- But test it out and adjust accordingly based on CSP quotas*
 - *CSPs have quotas on PPS, but often do not publish them





Gateway and Controller Upgrading & Updating



Types of Upgrades and Updates



Software Upgrade

- Replaces relevant Platform (i.e., Controller) and **selected** Gateway packages, configuration files, and binaries to Target version
- Part of regular maintenance operations
- Hitless

Image Upgrade

- Replaces selected Gateway cloud image (AMI, VHD, etc.) to the newer version
- Doesn't change Aviatrix software version
- Less frequent
- Incurs traffic disruption

Security Patches

- Released when security updates to underlying software components become available.
- Most security patches are hitless (review the release notes)

Software Patches


- Released to address compatibility issues when they arise (if you are using any applications or configurations affected by the patch.
- Most software patches are hitless (review the release notes)



Terminology



- Software Major, Minor, Build Release
 - Numbering convention
 - Example: Aviatrix Release 6.5.100





Supported Upgrade Paths



6.5.900 (latest)

- Upgrading Builds (within same minor release)
 - You automatically get the latest build and cannot select the build number.
 - Process might skip over previously released build numbers.
- Upgrading Minor Release Version (within same major release)
 - You must upgrade each minor release sequentially.
- Upgrading Major Release Version
 - You must upgrade each major release sequentially.



6.5.100





Software Rollback



- Software roll back to Gateway software previous version
- Previous version may or may not be the latest patch/build version available
- Replaces the entire Gateway (image + software) → expect brief disruption
- Gateway Image version may automatically be downgraded if required
- Does not apply to Controller

Upgrade Scenarios



- At any point in time, the Controller supports
 2 unique Gateway software versions:
 - Target Version: same version as the Controller
 - **Previous:** previous version of the Controller
- Example of supported scenario
 - Upgrade the Controller from 6.5 to 6.5.100
 - Upgrade a group of Gateways to 6.5.100
 - Remaining Gateways run 6.5


- Example of unsupported scenario
 - Upgrade the Controller from 6.5 to 6.5.100
 - Upgrade a group of Gateways to 6.5.100
 - Remaining Gateways run 6.5
 - Upgrade the Controller to 6.5.200
 - Not supported: All Gateways must be upgraded to 6.5.100 before upgrading the Controller to 6.5.200



Upgrade Groups (1)



- Each Upgrade Group that gets created is split up into two groups:
 - Primary Node Group
 - Secondary Nodes Group
- ☐ If you do want to get around that you will have to, after you have created the group, to manually update it to include additional ones. Likewise, If you want to do both primary and Secondary nodes at the same time.



Upgrade Plan and Upgrade Groups

You can now create Upgrade Groups of Gateways based on Cloud, Account, Region, or other criteria.


Each Upgrade Group will be automatically divided into two subgroups: one comprising High Availability (HA) instances and another comprising Primary instances.

Reorder the groups based on your preference to create your Upgrade Plan. Applicable for both Software and Image Upgrades.



Upgrade Groups (2)








Upgrade Groups (3)





Upgrade Groups (4)



+ Upgrade Group	Prepare For Upgrade	7 □ Φ				2 New 2 Modified	Discard	ommit Q Search		By Upgr × ~
Name	Gateway Type	Gateway Instance	Software Version	Image Version	Kernel Version	Account	Cloud	Region	Upgrade Group Status	
☐ Upgrade-Spoke-GW	Spoke	1	7.0.2239	hvm-cloudx-a	5.4.0-1096-aw	aws-account	AWS	eu-central-1	① Unknown	↑ / □
☐ Upgrade-Spoke-GW	Spoke	4	7.0.2239	[Multiple]	[Multiple]	[Multiple]	[Multiple]	[Multiple]	① Unknown	↑
☐ Unassigned HA	Transit	2	7.0.2239	[Multiple]	[Multiple]	[Multiple]	[Multiple]	[Multiple]		
☐ Unassigned Primar	Transit	2	7.0.2239	[Multiple]	[Multiple]	[Multiple]	[Multiple]	[Multiple]		

- ☐ After the Upgrade Group has been created, it will need to be committed before the upgrade gets started
- The **Edit** icon allows to modify the groups



Support Resources



Support Portal



- Aviatrix customers may visit Support portal https://support.aviatrix.com to access:
 - Knowledge Base with videos
 - Documentation
 - Community
 - History of tickets
 - CSP outage tracker
- Sign up for Email Notifications from Controller

Email Notifications

Manage the status of your Aviatrix system and ensure your teams receive important notification emails sent by Aviatrix.

Enter email aliases for teams that can respond to each type of alert. If you enter the same email for all four fields, that email account could be overwhelmed. Read more

The email aliases collected will solely be used for the purpose described here. For more information, please refer to our Privacy Policy

ACCOUNT AND CERTIFICATE ALERTS SECURITY EVENTS Receive important account and certification information. Receive security and CVE (Common Vulnerabilities and Exposures) notification emails. Administrator Email Alias Security Admin Email Alias ace.lab@aviatrix.com **VERIFY** security-admin-group@yourcompany.com VERIFY **CRITICAL ALERTS** STATUS CHANGE NOTIFICATIONS Receive field notices and critical notices. These alerts ensure that you can respond to urgent events. Receive system/tunnel status notification emails. IT Admin Email Alias IT Admin Email Alias it-support@yourcompany.com VERIFY it-admin-group@yourcompany.com VERIFY Status Change Notification Interval (seconds)

60





Next:

Let's troubleshoot together session

