

05. LEAFLET Zoom Levels.


5.1. Zoom level.

Leaflet works with **latitude**, **longitude** and "**zoom level**". Lower zoom levels means that the map shows entire continents, while higher zoom levels means that the map can show details of a city.

To understand how zoom levels work, first we need a basic introduction to geodesy.

5.2. The shape of the Earth.

Let's have a look at a simple map locked at zoom zero:






Notice that the "whole earth" is just one image, 256 pixels wide and 256 pixels high:



Just to be clear: the earth is not a square. So we assume that the earth is mosly round. To make it flat, we put an imaginary cylinder around, unroll it, and cut it so it looks square:



Things like geodesy, map projections and coordinate systems are hard, very hard (and out of scope for this tutorial). Assuming that the earth is a square is not always the right thing to do, but most of the time works fine enough, makes things simpler, and allows Leaflet (and other map libraries) to be fast.

5.3. Powers of Two

For now, let's just assume that the world is a square:





When we represent the world at zoom level zero, it's 256 pixels wide and high. When we go into zoom level one, it doubles its width and height, and can be represented by four 256-pixel-by-256-pixel images:



At each zoom level, each tile is divided in four, and its size (length of the edge, given by the *tileSize* option) doubles, quadrupling the area. (in other words, the width and height of the world is 256·2zoomlevel pixels):





This goes on and on. Most tile services offer tiles up to zoom level 18, depending on their coverage. This is enough to see a few city blocks per tile.

5.4. A note about scale

One of the disadvantages of using a cylindrical projection is that the scale is not constant, and measuring distances or sizes is not reliable, specially at low zoom levels.

In technical terms, the cylindrical projection that Leaflet uses is conformal (preserves shapes), but not equidistant (does not preserve distances), and not equal-area (does not preserve areas, as things near the equator appear smaller than they are).


By adding a **L.Control.Scale** to a map, and panning to the equator and to 60° north, we can see how the scale factor doubles. The following example uses javascript timeouts to do this automatically:

Example:

```
L.control.scale().addTo(map);

setInterval(function() {
    map.setView([0, 0]);
    setTimeout(function() {
        map.setView([60, 0]);
    }, 2000);
}, 4000);
```





L.Control.Scale shows the scale which applies to the center point of the map. At high zoom levels, the scale changes very little, and is not noticeable.

5.5. Controlling the zoom

A leaflet map has several ways to control the zoom level shown, but the most obvious one is setZoom(). For example, map.setZoom(0); will set the zoom level of map to 0.

This example again uses timeouts to alternate between zoom levels 0 and 1 automatically:

Example:

```
setInterval(function() {
    map.setZoom(0);
    setTimeout(function() {
        map.setZoom(1);
    }, 2000);
}, 4000);
```





Notice how the images shown at zoom levels 0 and one correspond with the images shown in the previous section!

Other ways of setting the zoom are:

- setView(center, zoom), which also sets the map center
- **flyTo(center, zoom)**, like setView but with a smooth animation
- zoomIn() / zoomIn(delta), zooms in delta zoom levels, 1 by default
- **zoomOut()** / **zoomOut(delta)**, zooms out delta zoom levels, 1 by default
- **setZoomAround(fixedPoint, zoom)**, sets the zoom level while keeping a point fixed (what scrollwheel zooming does)
- fitBounds(bounds), automatically calculates the zoom to fit a rectangular area on the map

5.6. Fractional zoom

A feature introduced in Leaflet 1.0.0 was the concept of fractional zoom. Before this, the zoom level of the map could be only an integer number (0, 1, 2, and so on); but now you can use fractional numbers like 1.5 or 1.25.

Fractional zoom is disabled by default. To enable it, use the map's **zoomSnap** option. The zoomSnap option has a default value of 1 (which means that the zoom level of the map can be 0, 1, 2, and so on).


If you set the value of *zoomSnap* to 0.5, the valid zoom levels of the map will be 0, 0.5, 1, 1.5, 2, and so on. If you set a value of 0.1, the valid zoom levels of the map will be 0, 0.1, 0.2, 0.3, 0.4, and so on.

The following example uses a **zoomSnap** value of 0.25:



Example:

```
var map = L.map('map', {
         zoomSnap: 0.25
});
```



As you can see, Leaflet will only load the tiles for zoom levels 0 or 1, and will scale them as needed.

Leaflet will snap the zoom level to the closest valid one. For example, if you have **zoomSnap**: 0.25 and you try to do **map.setZoom(0.8)**, the zoom will snap back to 0.75. The same happens with **map.fitBounds(bounds)**, or when ending a pinch-zoom gesture on a touchscreen.

zoomSnap can be set to zero. This means that Leaflet will not snap the zoom level.

There is another important map option related to *zoomSnap*: the *zoomDelta* option. This controls how many zoom levels to zoom in/out when using the zoom buttons (from the default *L.Control.Zoom*) or the +/- keys in your keyboard.

For the *mousewheel* zoom, the *wheelPxPerZoomLevel* option controls how fast the mousewheel zooms in our out. Here is an example with zoomSnap set to zero:

Example:

```
var map = L.map('map', {
          zoomDelta: 0.25,
          zoomSnap: 0
});
```



Try the following, and see how the zoom level changes:

- Pinch-zoom if you have a touchscreen
- **Zoom in/out** with your mousewheel
- Do a box zoom (drag with your mouse while pressing the shift key in your keyboard)
- Use the zoom in/out buttons

