Ubuntu 安装 Mysql 数据库

首先更新apt-get工具,执行命令如下:

apt-get upgrade

```
(base) root@4U:-a apt-get upgrade

Reading package lists... Done

Building dependency tree... Done

Reading state information... Done

Calculating upgrade... Done

The following packages were automatically installed and are no longer required:

bridge-utils cuda-cccl-il-8 cuda-command-line-tools-il-8 cuda-compiler-il-8 cuda-udart-il-8 cuda-might-il-8 cuda-night-il-8 cuda-norprune-il-8 cuda-invaries-il-8 cuda-norprune-il-8 cuda-invaries-il-8 cuda-norprune-il-8 libcurand-il-8 libcu
```

安装Mysql, 执行如下命令:

apt-get install mysql-server

开启Mysql 服务,执行命令如下:

```
service mysql start
```

并确认是否成功开启mysql,执行命令如下:

```
service mysql status
```

```
(base) root@4U:~# service mysql start
(base) root@4U:~# service mysql status

mysql.service - MySQL Community Server
Loaded: loaded (/lib/systemd/system/mysql.service; enabled; vendor preset: enabled)
Active: active (running) since Tue 2024-06-04 10:45:33 CST; 3min 9s ago
Process: 3820578 ExecStartPre=/usr/share/mysql/mysql-systemd-start pre (code=exited, status=0/SUCCESS)
Main PID: 3820586 (mysqld)
Status: "Server is operational"
Tasks: 37 (limit: 231379)
Memory: 352.7M
CPU: 2.525s
CGroup: /system.slice/mysql.service
L3820586 /usr/sbin/mysqld

6月 04 10:45:32 4U systemd[1]: Starting MySQL Community Server...
6月 04 10:45:33 4U systemd[1]: Started MySQL Community Server.
(base) root@4U:~# []
```

确认是否启动成功,在LISTEN状态下,启动成功:

```
netstat -tap | grep mysql
```

在最新使用的 MySQL 版本中,默认使用 auth_socket 插件来进行身份验证,这意味着 root 用户通过操作系统的用户身份进行认证,而不是使用密码。这种配置在许多 Linux 系统上是默认的,特别是在安装 MySQL 时不要求设置密码的情况下。如果我们希望使用传统的密码验证方式来登录 MySQL,需要更改 root 用户的认证方式。以下是如何将 root 用户从 auth socket 插件更改为使用密码认证的步骤:

1. 登录 MySQL:

首先,使用以下命令登录到 MySQL:

```
sudo mysql
```

```
(base) root@4U:~

sudo mysql

Welcome to the MySQL monitor. Commands end with ; or \g.

Your MySQL connection id is 10

Server version: 8.0.36-Oubuntu0.20.04.1 (Ubuntu)

Copyright (c) 2000, 2024, Oracle and/or its affiliates.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.

mysql>

■
```

2. 更改认证插件和设置密码:

在 MySQL 命令行中,使用以下命令来更改 root 用户的认证插件并设置一个新密码:

```
ALTER USER 'root'@'localhost' IDENTIFIED WITH mysql_native_password BY '新密码'; FLUSH PRIVILEGES;
```

把「新密码」替换为你想要设置的密码。

```
mysql> ALTER USER 'root'@'localhost' IDENTIFIED WITH mysql_native_password BY 'Snc...cacco. )&@(';
Query OK, 0 rows affected (0.02 sec)

mysql> FLUSH PRIVILEGES:
Query OK, 0 rows affected (0.02 sec)

mysql> |
```

3. 退出并测试登录:

更改完成后,退出 MySQL:

```
exit;
```

然后尝试使用新密码重新登录:

```
sudo mysql -u root -p
```

系统将提示你输入密码,此时应输入你刚才设置的密码。

```
(base) root@4U:-# sudo mysql -u root -p
Enter password:
Welcome to the MySQL monitor. Commands end with ; or \g.
Your MySQL connection id is 14
Server version: 8.0.36-Oubuntu0.20.04.1 (Ubuntu)

Copyright (c) 2000, 2024, Oracle and/or its affiliates.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.

mysql>
```

MySQL 配置文件中的 bind-address 参数限制了可以接受连接的 IP 地址。需要确认它是否设置为允许 从你的客户端 IP 访问。查看 /etc/mysql/mysql.conf.d/mysqld.cnf 文件中的 bind-address:

```
(base) root@4U:~# vim /etc/mysql/mysql.conf.d/mysqld.cnf
(base) root@4U:~#
```

如果设置为 127.0.0.1(只允许本地连接),需要改为 0.0.0.0(允许任何 IP 连接)或具体的外部 IP 地址,然后重启 MySQL 服务:

```
[mysqld]
# * Basic Settings
              = mysql
user
# pid-file = /var/run/mysqld/mysqld.pid
             = /var/run/mysqld/mysqld.sock
# socket
# port
# datadir
             = /var/lib/mysql
# If MySQL is running as a replication slave, this should be
# changed. Ref https://dev.mysql.com/doc/refman/8.0/en/server-system-variables.
# tmpdir
                      = /tmp
# Instead of skip-networking the default is now to listen only on
# localhost which is more compatible and is not less secure.
bind-address = 0.0.0.0
mysglx-bind-address = 127.0.0.1
# * Fine Tuning
key buffer size
                     = 16M
# max allowed packet
                     = 64M
                      = 256K
# thread stack
# thread cache size
```

```
sudo systemctl restart mysql
```

再次登录Mysql,确保 MySQL 用户的主机设置允许从你的客户端 IP 地址连接。可以在 MySQL 中运行以下 SQL 命令来检查:

```
(base) root@4U:~# vim /etc/mysql/mysql.conf.d/mysqld.cnf
(base) root@4U:~# vim /etc/mysql/mysql.conf.d/mysqld.cnf
(base) root@4U:~# sudo systemctl restart mysql

(base) root@4U:~#
```

接下来,我们需要使用 root 用户或具有相应权限的用户登录到 MySQL。可以通过以下命令登录:

```
mysql -u root -p
```

登录后,需要选择 mysql 数据库,因为用户信息存储在这个数据库中:

```
USE mysql;
```

执行以下 SQL 命令来查看所有用户及其主机:

```
SELECT user, host FROM user;
```

决定修改现有用户(如 root 用户),可以更改用户的 host 值,以允许从任意 IP 地址连接。执行如下命令:

```
UPDATE user SET host = '%' WHERE user = 'root' AND host = 'localhost';
FLUSH PRIVILEGES
```

这里将 root 用户的 host 从 localhost 改为 %,表示从任何 IP 地址都允许连接。

```
mysql> UPDATE user SET host = '%' WHERE user = 'root' AND host = 'localhost';
Query UK, 1 row affected (0.01 sec)
Rows matched: 1 Changed: 1 Warnings: 0

mysql> FLUSH PRIVILEGES;
Query OK, 0 rows affected (0.01 sec)

mysql> |
```

Windows下载Navicat, 地址: https://www.navicat.com/en/download/direct-download?product=n avicat170 premium en x64.exe&location=1




Download Trial


We offer a 14-day fully functional FREE trial of Navicat.




选择Connection:




新建一个Mysql连接:



输入远程服务器的IP, Mysql的用户名和密码, 执行连通性测试。



如何能够正常连接,会提示 Connection Successful 字样。



接下来就可以正常在Navinate工具中进行Mysql操作了。

