Crowdcoin Masternode Setup Guide on UBUNTU VPS Server

We need at least 1GHz and 2GB of Ram, if you don't have enough ram you can do a swap file

For this you can use these step by step guide here

Before anything set up initial server using this guide here

List of things that are essential:

- 1. 1000CRC (+1 CRC to cover any TX fees)
- 2. IP address
- 3. And the Obvious a VPS server

Now we are Ready to do the Node

Step 1: Install the packages

sudo apt-get install build-essential libtool automake autoconf sudo apt-get install autotools-dev autoconf pkg-config libssl-dev sudo apt-get install libgmp3-dev libevent-dev bsdmainutils libboost-all-dev sudo add-apt-repository ppa:bitcoin/bitcoin sudo apt-get update sudo apt-get install libdb4.8-dev libdb4.8++-dev sudo apt-get install libminiupnpc-dev

Step 2: Build the Wallet

Clone the git from here: https://github.com/crowdcoinChain/Crowdcoin

sudo apt-get install git git clone https://github.com/crowdcoinChain/Crowdcoin.git

Step 3: Go to the Crowdcoin folder that you have created and execute this:

cd Crowdcoin chmod 755 autogen.sh ./autogen.sh ./configure chmod 755 share/genbuild.sh make

Step 3: Start Headless Client

cd src ./Crowdcoin -daemon

Now we are going back to our Windows Wallet the Local wallet that you keep your coins

Step 1: Go to the wallet Tools-> Debug Konsole and enter

getnewaddress MN1

Copy the address that it give you

Step 2: Send 1000crc to the address that you copied

Wait for 1 Confirmation

Then go to Debug Console again and type

masternode outputs

Now you should see 2 lines

tx id

digit

Save these 2 lines to a Text document

I assume you have the debug console open type masternode genkey this is your masternode privat key copy it in a text document we will be needing it later

Step 3: Go to your Crowdcoin data directory it is usualy in

C:\Users\user1\AppData\Roaming\CrowdcoinCore

Open the masternode.conf and type

MN1 IP: 12865 masternodeprivkey tx id digit

Save and close

Ok now we are going Back to our Server wallet

Go to crowdcoin folder by typing

cd /home/user/.CrowdcoinCore

The *user* corresponds to your computer username in which you are logged in.

nano crowdcoin.conf

Now copy and paste these

```
rpcuser=user
rpcpassword=pass
rpcallowip=127.0.0.1
listen=1
server=1
daemon=1
staking=0
externalip=IP: 12865
masternode=1
masternodeprivkey=masternodeprivkey
```

Username and pass can be of your choice

IP should be your VPS IP address

The Port should always be 12865

The masternodkey is the one that you have copied paste it there

Now Ctrl+X then Y then Enter

Execute that sudo ufw allow 12865/tcp

Note that you have to open the port 12865

Now start the masternode by navigating to your folder

```
cd
cd Crowdcoin/src/
./crowdcoind -daemon
```

Wait 15 minutes

After that go back to the main Wallet then go to Masternode Tab and click Start Allias and your masternode should be up

Notel You must w8 for at least 15 Confimartion before starting the masternode

Note2 You can check the status of your Masternode by going to your VPS wallet and typing $\,$

./crowdcoin-cli masternode status