

# **Configure node-scoped NDMP**

ONTAP 9

NetApp May 12, 2022

This PDF was generated from https://docs.netapp.com/us-en/ontap/ndmp/enable-node-scoped-ndmp-cluster-task.html on May 12, 2022. Always check docs.netapp.com for the latest.

## **Table of Contents**

Configure node-scoped NDMP	
Enable node-scoped NDMP on the cluster	
Configure a LIF	

## **Configure node-scoped NDMP**

### **Enable node-scoped NDMP on the cluster**

You can back up volumes hosted on a node by enabling node-scoped NDMP, setting up the password for the root user, and configuring a LIF for data and control connection.

You can configure node-scoped NDMP by enabling node-scoped NDMP on the cluster and NDMP service on all nodes of the cluster. You must also configure the root user for NDMP when enabling the NDMP service.

#### Steps

1. Enable node-scoped NDMP mode by using the system services ndmp command with the node-scope-mode parameter.

```
cluster1::> system services ndmp node-scope-mode on
NDMP node-scope-mode is enabled.
```

2. Enable NDMP service on all nodes in the cluster by using the system services ndmp on command.

Using the wildcard "\*" enables NDMP service on all nodes at the same time.

You must specify a password for authentication of the NDMP connection by the backup application.

```
cluster1::> system services ndmp on -node *

Please enter password:
Confirm password:
2 entries were modified.
```

 Disable the -clear-text option for secure communication of the NDMP password by using the system services ndmp modify command.

Using the wildcard "\*" disables the -clear-text option on all nodes at the same time.

```
cluster1::> system services ndmp modify -node * -clear-text false
2 entries were modified.
```

4. Verify that NDMP service is enabled and the -clear-text option is disabled by using the system services ndmp show command.

### **Configure a LIF**

You must identify a LIF that will be used for establishing a data connection and control connection between the node and the backup application. After identifying the LIF, you must verify that firewall and failover policies are set for the LIF.

#### **Steps**

1. Identify the intercluster LIF hosted on the nodes by using the network interface show command with the -role parameter.

cluster1::> network interface show -role intercluster							
Current Is	Logical	Status	Network	Current			
Vserver Home	Interface	Admin/Oper	Address/Mask	Node	Port		
cluster1	IC1	up/up	192.0.2.65/24	cluster1-1	e0a		
cluster1 true	IC2	up/up	192.0.2.68/24	cluster1-2	e0b		

- 2. Ensure that the firewall policy is enabled for NDMP on the intercluster LIFs:
  - a. Verify that the firewall policy is enabled for NDMP by using the system services firewall policy show command.

The following command displays the firewall policy for the intercluster LIF:

```
cluster1::> system services firewall policy show -policy intercluster
Vserver
        Policy
                   Service Allowed
_____
         _____
        intercluster dns
cluster1
                   http
                   https
                           0.0.0.0/0, ::/0**
                   **ndmp
                   ndmps
                   ntp
                   rsh
                   ssh
                   telnet -
9 entries were displayed.
```

b. If the firewall policy is not enabled, enable the firewall policy by using the system services firewall policy modify command with the -service parameter.

The following command enables firewall policy for the intercluster LIF:

```
cluster1::> system services firewall policy modify -vserver cluster1
-policy intercluster -service ndmp 0.0.0.0/0
```

- 3. Ensure that the failover policy is set appropriately for the intercluster LIFs:
  - a. Verify that the failover policy for the intercluster LIFs is set to local-only by using the network interface show -failover command.

```
cluster1::> network interface show -failover
                        Home
         Logical
                                         Failover
                                                    Failover
Vserver Interface Node:Port Policy
                                                     Group
         **IC1
cluster1
                           cluster1-1:e0a local-only
Default**
                                              Failover Targets:
                                              . . . . . . .
          **IC2
                    cluster1-2:e0b
                                            local-only
Default**
                                              Failover Targets:
                                              . . . . . . .
cluster1-1 cluster1-1 mgmt1 cluster1-1:e0m local-only Default
                                              Failover Targets:
                                              . . . . . . .
```

b. If the failover policy is not set appropriately, modify the failover policy by using the network interface modify command with the -failover-policy parameter.

cluster1::> network interface modify -vserver cluster1 -lif IC1
-failover-policy local-only

#### **Copyright Information**

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

#### **Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at <a href="http://www.netapp.com/TM">http://www.netapp.com/TM</a> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.