# Audio Queue Services Reference

Audio & Video: Audio



ć

Apple Inc. © 2011 Apple Inc. All rights reserved. Some states do not allow the exclusion or limitation of implied warranties or liability for incidental or consequential damages, so the above limitation or exclusion may not apply to you. This warranty gives you specific legal rights, and you may also have other rights which vary from state to state.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, mechanical, electronic, photocopying, recording, or otherwise, without prior written permission of Apple Inc., with the following exceptions: Any person is hereby authorized to store documentation on a single computer for personal use only and to print copies of documentation for personal use provided that the documentation contains Apple's copyright notice.

The Apple logo is a trademark of Apple Inc.

No licenses, express or implied, are granted with respect to any of the technology described in this document. Apple retains all intellectual property rights associated with the technology described in this document. This document is intended to assist application developers to develop applications only for Apple-labeled computers.

Apple Inc. 1 Infinite Loop Cupertino, CA 95014 408-996-1010

Apple, the Apple logo, iPhone, Mac, and Mac OS are trademarks of Apple Inc., registered in the United States and other countries.

IOS is a trademark or registered trademark of Cisco in the U.S. and other countries and is used under license.

Times is a registered trademark of Heidelberger Druckmaschinen AG, available from Linotype Library GmbH.

Even though Apple has reviewed this document, APPLE MAKES NO WARRANTY OR REPRESENTATION, EITHER EXPRESS OR IMPLIED, WITH RESPECT TO THIS DOCUMENT, ITS QUALITY, ACCURACY, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. AS A RESULT, THIS DOCUMENT IS PROVIDED "AS IS," AND YOU, THE READER, ARE ASSUMING THE ENTIRE RISK AS TO ITS QUALITY AND ACCURACY.

IN NO EVENT WILL APPLE BE LIABLE FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES RESULTING FROM ANY DEFECT OR INACCURACY IN THIS DOCUMENT, even if advised of the possibility of such damages.

THE WARRANTY AND REMEDIES SET FORTH ABOVE ARE EXCLUSIVE AND IN LIEU OF ALL OTHERS, ORAL OR WRITTEN, EXPRESS OR IMPLIED. No Apple dealer, agent, or employee is authorized to make any modification, extension, or addition to this warranty.

## **Contents**

### **Audio Queue Services Reference** 5

```
Overview 5
Functions by Task 5
  Controlling Audio Queues 5
  Creating and Disposing of Audio Queues 6
  Handling Audio Queue Buffers 6
  Manipulating Audio Queue Parameters 6
  Manipulating Audio Queue Properties 7
  Handling Timing 7
  Performing Offline Rendering 7
Functions 8
  AudioQueueAddPropertyListener 8
  AudioQueueAllocateBuffer 8
  AudioQueueAllocateBufferWithPacketDescriptions 9
  AudioQueueCreateTimeline 10
  AudioQueueDeviceGetCurrentTime 11
  AudioQueueDeviceGetNearestStartTime 11
  AudioQueueDeviceTranslateTime 12
  AudioQueueDispose 13
  AudioQueueDisposeTimeline 13
  AudioQueueEnqueueBuffer 14
  AudioQueueEnqueueBufferWithParameters 15
  AudioOueueFlush 17
  AudioQueueFreeBuffer 18
  AudioQueueGetCurrentTime 18
  AudioQueueGetParameter 19
  AudioQueueGetProperty 20
  AudioQueueGetPropertySize 21
  AudioQueueNewInput 21
  AudioQueueNewOutput 22
  AudioQueueOfflineRender 23
  AudioQueuePause 24
  AudioQueuePrime 25
  AudioQueueRemovePropertyListener 25
  AudioQueueReset 26
  AudioQueueSetOfflineRenderFormat 27
  AudioQueueSetParameter 28
  AudioQueueSetProperty 28
  AudioQueueStart 29
  AudioQueueStop 30
Callbacks by Task 31
```

```
Handling Audio Queue Buffers for Recording and Playback 31
  Defining a Property Listener 31
Callbacks 31
  AudioQueueInputCallback 31
  AudioQueueOutputCallback 32
  AudioQueuePropertyListenerProc 33
Data Types 34
  AudioQueueBuffer 34
  AudioQueueBufferRef 35
  AudioQueueRef 35
  AudioQueueTimelineRef 36
  AudioQueueLevelMeterState 36
  AudioQueueParameterEvent 37
  AudioQueueParameterID 37
  AudioQueueParameterValue 37
Constants 38
  Audio Queue Property Identifiers 38
  Audio Queue Parameters 40
  Hardware Codec Policy Keys 41
Result Codes 42
```

**Document Revision History 45** 

# **Audio Queue Services Reference**

Framework: AudioToolbox/AudioToolbox.h

**Declared in** AudioQueue.h

## Overview

This document describes Audio Queue Services, a C programming interface in the Audio Toolbox framework, which is part of Core Audio.

An audio queue is a software object you use for recording or playing audio. An audio queue does the work of:

- Connecting to audio hardware
- Managing memory
- Employing codecs, as needed, for compressed audio formats
- Mediating playback or recording

Audio Queue Services enables you to record and play audio in linear PCM, in compressed formats (such as Apple Lossless and AAC), and in other formats for which users have installed codecs. Audio Queue Services also supports scheduled playback and synchronization of multiple audio queues and synchronization of audio with video.

**Note:** Audio Queue Services provides features similar to those previously offered by the Sound Manager and in Mac OS X. It adds additional features such as synchronization. The Sound Manager is deprecated in Mac OS X v10.5 and does not work with 64-bit applications. Audio Queue Services is recommended for all new development and as a replacement for the Sound Manager in existing Mac OS X applications.

## Functions by Task

## **Controlling Audio Queues**

AudioQueueStart (page 29)

Begins playing or recording audio.

```
AudioQueuePrime (page 25)
```

Decodes enqueued buffers in preparation for playback.

AudioQueueFlush (page 17)

Resets an audio queue's decoder state.

AudioQueueStop (page 30)

Stops playing or recording audio.

AudioQueuePause (page 24)

Pauses audio playback or recording.

AudioQueueReset (page 26)

Resets an audio queue.

## **Creating and Disposing of Audio Queues**

AudioQueueNewOutput (page 22)

Creates a new playback audio queue object.

AudioQueueNewInput (page 21)

Creates a new recording audio queue object.

AudioQueueDispose (page 13)

Disposes of an audio queue.

## **Handling Audio Queue Buffers**

AudioQueueAllocateBuffer (page 8)

Asks an audio queue object to allocate an audio queue buffer.

AudioQueueAllocateBufferWithPacketDescriptions (page 9)

Asks an audio queue object to allocate an audio queue buffer with space for packet descriptions.

AudioQueueFreeBuffer (page 18)

Asks an audio queue to dispose of an audio queue buffer.

AudioQueueEnqueueBuffer (page 14)

Adds a buffer to the buffer queue of a recording or playback audio queue.

AudioQueueEngueueBufferWithParameters (page 15)

Adds a buffer to the buffer queue of a playback audio queue object, specifying start time and other settings.

## **Manipulating Audio Queue Parameters**

AudioQueueGetParameter (page 19)

Gets an audio queue parameter value.

AudioQueueSetParameter (page 28)

Sets a playback audio queue parameter value.

## **Manipulating Audio Queue Properties**

AudioQueueGetProperty (page 20)

Gets an audio queue property value.

AudioQueueSetProperty (page 28)

Sets an audio queue property value.

AudioQueueGetPropertySize (page 21)

Gets the size of the value of an audio queue property.

AudioQueueAddPropertyListener (page 8)

Adds a property listener callback to an audio queue.

AudioQueueRemovePropertyListener (page 25)

Removes a property listener callback from an audio queue.

## **Handling Timing**

AudioQueueCreateTimeline (page 10)

Creates a timeline object for an audio queue.

AudioQueueDisposeTimeline (page 13)

Disposes of an audio queue's timeline object.

AudioQueueDeviceGetCurrentTime (page 11)

Gets the current time of the audio hardware device associated with an audio queue.

AudioQueueDeviceGetNearestStartTime (page 11)

Gets the start time, for an audio hardware device, that is closest to a requested start time.

AudioQueueDeviceTranslateTime (page 12)

Converts the time for an audio queue's associated audio hardware device from one time base representation to another.

AudioQueueGetCurrentTime (page 18)

Gets the current audio queue time.

## **Performing Offline Rendering**

AudioQueueSetOfflineRenderFormat (page 27)

Sets the rendering mode and audio format for a playback audio queue.

AudioQueueOfflineRender (page 23)

Exports audio to a buffer, instead of to a device, using a playback audio queue.

## **Functions**

### AudioQueueAddPropertyListener

Adds a property listener callback to an audio queue.

```
OSStatus AudioQueueAddPropertyListener (
    AudioQueueRef inAQ,
    AudioQueuePropertyID inID,
    AudioQueuePropertyListenerProc inProc,
    void *inUserData
);
```

#### **Parameters**

inA0

The audio queue that you want to assign a property listener callback to.

inID

The ID of the property whose changes you want to respond to. See "Audio Queue Property Identifiers" (page 38).

inProc

The callback to be invoked when the property value changes.

inUserData

Custom data for the property listener callback.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

### Discussion

Use this function to let your application respond to property value changes in an audio queue. For example, say your application's user interface has a button that acts as a Play/Stop toggle switch. When an audio file has finished playing, the audio queue stops and the value of the kAudioQueueProperty\_IsRunning property changes from true to false. You can use a property listener callback to update the button text appropriately.

#### **Availability**

Available in iOS 2.0 and later.

#### See Also

AudioQueueRemovePropertyListener (page 25)

### **Related Sample Code**

SpeakHere

#### **Declared In**

AudioQueue.h

### AudioQueueAllocateBuffer

Asks an audio queue object to allocate an audio queue buffer.

```
OSStatus AudioQueueAllocateBuffer (
   AudioQueueRef inAQ,
   UInt32 inBufferByteSize,
   AudioQueueBufferRef *outBuffer
);
```

#### **Parameters**

inA0

The audio queue you want to allocate a buffer.

```
inBufferByteSize
```

The desired capacity of the new buffer, in bytes. Appropriate capacity depends on the processing you will perform on the data as well as on the audio data format.

outBuffer

On output, points to the newly allocated audio queue buffer.

#### Return Value

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

Once allocated, the pointer to the audio queue buffer and the buffer's capacity cannot be changed. The buffer's size field, mAudioDataByteSize, which indicates the amount of valid data, is initially set to 0.

### **Availability**

Available in iOS 2.0 and later.

### See Also

```
AudioQueueAllocateBufferWithPacketDescriptions (page 9)
AudioQueueFreeBuffer (page 18)
```

### **Related Sample Code**

AQOfflineRenderTest

SpeakHere

#### **Declared In**

AudioOueue.h

## Audio Queue Allocate Buffer With Packet Descriptions

Asks an audio queue object to allocate an audio queue buffer with space for packet descriptions.

```
AudioQueueAllocateBufferWithPacketDescriptions(
    AudioQueueRef inAQ,
    UInt32 inBufferByteSize,
    UInt32 inNumberPacketDescriptions,
    AudioQueueBufferRef *outBuffer
):
```

#### **Parameters**

inAQ

The audio queue you want to allocate a buffer.

```
inBufferByteSize
```

The desired data capacity of the new buffer, in bytes. Appropriate capacity depends on the processing you will perform on the data as well as on the audio data format.

```
inNumberPacketDescriptions
```

The desired size of the packet description array in the new audio queue buffer.

outBuffer

On output, points to the newly allocated audio queue buffer.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

Use this function when allocating an audio queue buffer for use with a VBR compressed data format.

Once allocated, the pointer to the audio queue buffer and the buffer's capacity cannot be changed. The buffer's size field, mAudioDataByteSize, which indicates the amount of valid data, is initially set to 0.

### **Availability**

Available in iOS 2.0 and later.

#### See Also

```
AudioQueueAllocateBuffer (page 8)
AudioQueueFreeBuffer (page 18)
```

### **Related Sample Code**

SpeakHere

#### **Declared In**

AudioOueue.h

### **AudioOueueCreateTimeline**

Creates a timeline object for an audio queue.

```
OSStatus AudioQueueCreateTimeline (
   AudioQueueRef inAQ,
   AudioQueueTimelineRef *outTimeline
):
```

### **Parameters**

inAQ

The audio queue to associate with the new timeline object.

outTimeLine

On output, the newly created timeline object.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

### Discussion

Create a timeline object if you want to get timeline discontinuity information from an audio queue using the AudioQueueGetCurrentTime (page 18) function.

#### **Availability**

Available in iOS 2.0 and later.

#### See Also

AudioQueueDisposeTimeline (page 13)

AudioQueueGetCurrentTime (page 18)

#### **Declared In**

AudioQueue.h

### AudioQueueDeviceGetCurrentTime

Gets the current time of the audio hardware device associated with an audio queue.

```
OSStatus AudioQueueDeviceGetCurrentTime (
   AudioQueueRef inAQ,
   AudioTimeStamp *outTimeStamp
);
```

### **Parameters**

inA0

The audio queue whose associated audio device is to be queried.

outDeviceTime

On output, the current time of the audio hardware device associated with the audio queue. If the device is not running, the only valid field in the audio timestamp structure is mHostTime.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

This function returns a value whether or not the audio hardware device associated with the audio queue is running. The similar AudioDeviceGetCurrentTime function, declared in the AudioHardware.h header file, returns an error in this case.

### **Availability**

Available in iOS 2.0 and later.

#### See Also

AudioQueueGetCurrentTime (page 18)

### **Declared In**

AudioQueue.h

### **AudioQueueDeviceGetNearestStartTime**

Gets the start time, for an audio hardware device, that is closest to a requested start time.

```
OSStatus AudioQueueDeviceGetNearestStartTime (
   AudioQueueRef inAQ,
   AudioTimeStamp *ioRequestedStartTime,
   UInt32 inFlags
);
```

### **Parameters**

inA0

The audio queue whose associated audio hardware device's start time you want to get.

ioRequestedDeviceTime

On input, the requested start time. On output, the actual start time.

Functions

```
inFlags
```

Reserved for future use. Pass 0.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

This function asks an audio queue's associated device for a start time to use for recording or playback. The time returned will be equal to or later than the requested start time, depending on device and system factors. For example, the start time might be shifted to allow for aligning buffer access. The device must be running to use this function.

### **Availability**

Available in iOS 2.0 and later.

#### See Also

AudioQueueDeviceGetCurrentTime (page 11)

#### **Declared In**

AudioQueue.h

### **AudioQueueDeviceTranslateTime**

Converts the time for an audio queue's associated audio hardware device from one time base representation to another.

```
OSStatus AudioQueueDeviceTranslateTime (
   AudioQueueRef inAQ,
   const AudioTimeStamp *inTime,
   AudioTimeStamp *outTime
);
```

#### **Parameters**

inAQ

The audio queue associated with the device whose times are being translated.

inDeviceTime

The time to be translated.

outDeviceTime

On output, the translated time.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

### Discussion

The device must be running for this function to provide a result. For an explanation of the various time base representations for an audio hardware device, see AudioTimeStamp in Core Audio Data Types Reference.

### **Availability**

Available in iOS 2.0 and later.

#### Declared In

AudioQueue.h

### AudioQueueDispose

Disposes of an audio queue.

```
OSStatus AudioQueueDispose (
   AudioQueueRef inAQ,
   Boolean inImmediate
);
```

### **Parameters**

inA0

The audio queue you want to dispose of.

inImmediate

If you pass true, the audio queue is disposed of immediately (that is, synchronously). If you pass false, disposal does not take place until all enqueued buffers are processed (that is, asynchronously).

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

Disposing of an audio queue also disposes of its resources, including its buffers. After you call this function, you can no longer interact with the audio queue. In addition, the audio queue no longer invokes any callbacks.

### **Availability**

Available in iOS 2.0 and later.

### See Also

AudioQueueFlush (page 17)

### **Related Sample Code**

AQOfflineRenderTest

SpeakHere

### **Declared In**

AudioOueue.h

### AudioQueueDisposeTimeline

Disposes of an audio queue's timeline object.

```
OSStatus AudioQueueDisposeTimeline (
   AudioQueueRef inAQ,
   AudioQueueTimelineRef inTimeline
);
```

#### **Parameters**

inAQ

The audio queue associated with the timeline object you want to dispose of.

inTimeLine

The timeline object to dispose of.

### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

Disposing of an audio queue automatically disposes of any associated resources, including a timeline object. Call this function only if you want to dispose of a timeline object and not the audio queue associated with it.

#### **Availability**

Available in iOS 2.0 and later.

#### See Also

```
AudioQueueCreateTimeline (page 10)
AudioQueueDispose (page 13)
```

#### Declared In

AudioOueue.h

### AudioQueueEnqueueBuffer

Adds a buffer to the buffer queue of a recording or playback audio queue.

```
OSStatus AudioQueueEnqueueBuffer (
   AudioQueueRef inAQ,
   AudioQueueBufferRef inBuffer,
   UInt32 inNumPacketDescs,
   const AudioStreamPacketDescription *inPacketDescs);
```

#### **Parameters**

inA0

The audio queue that owns the audio queue buffer.

inBuffer

The audio queue buffer to add to the buffer queue.

inNumPacketDescs

The number of packets of audio data in the inBuffer parameter. Use a value of 0 for any of the following situations:

- When playing a constant bit rate (CBR) format.
- When the audio queue is a recording (input) audio queue.
- When the buffer you are reenqueuing was allocated with the
   AudioQueueAllocateBufferWithPacketDescriptions (page 9) function. In this case,
   your callback should describe the buffer's packets in the buffer's mPacketDescriptions and
   mPacketDescriptionCount fields.

#### inPacketDescs

An array of packet descriptions. Use a value of NULL for any of the following situations:

- When playing a constant bit rate (CBR) format.
- When the audio queue is an input (recording) audio queue.
- When the buffer you are reenqueuing was allocated with the AudioQueueAllocateBufferWithPacketDescriptions (page 9) function. In this case, your callback should describe the buffer's packets in the buffer's mPacketDescriptions and mPacketDescriptionCount fields.

#### Return Value

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

Audio queue callbacks use this function to reenqueue buffers—placing them "last in line" in a buffer queue. A playback (or *output*) callback reenqueues a buffer after the buffer is filled with fresh audio data (typically from a file). A recording (or *input*) callback reenqueues a buffer after the buffer's contents were written (typically to a file).

### **Availability**

Available in iOS 2.0 and later.

#### See Also

AudioQueueEnqueueBufferWithParameters (page 15)

### **Related Sample Code**

AQOfflineRenderTest SpeakHere

### Declared In

AudioOueue.h

### AudioQueueEnqueueBufferWithParameters

Adds a buffer to the buffer queue of a playback audio queue object, specifying start time and other settings.

```
OSStatus AudioQueueEngueueBufferWithParameters (
   AudioOueueRef
                                        inAQ,
   AudioQueueBufferRef
                                        inBuffer.
                                        inNumPacketDescs,
   const AudioStreamPacketDescription *inPacketDescs,
  UInt32
                                        inTrimFramesAtStart,
  UInt32
                                        inTrimFramesAtEnd,
  UInt32
                                        inNumParamValues,
   const AudioQueueParameterEvent
                                        *inParamValues.
  const AudioTimeStamp
                                        *inStartTime.
   AudioTimeStamp
                                        *outActualStartTime
);
```

### **Parameters**

inAQ

The audio queue object that owns the audio queue buffer.

#### inBuffer

The audio queue buffer to add to the buffer queue. Before calling this function, the buffer must contain the audio data to be played.

#### inNumPacketDescs

The number of packets of audio data in the inBuffer parameter. Use a value of 0 for either of the following situations:

- When playing a constant bit rate (CBR) format.
- When the buffer you are reenqueuing was allocated with the
   AudioQueueAllocateBufferWithPacketDescriptions (page 9) function. In this case,
   your callback should describe the buffer's packets in the buffer's mPacketDescriptions and
   mPacketDescriptionCount fields.

#### inPacketDescs

An array of packet descriptions. Use a value of NULL for either of the following situations:

- When playing a constant bit rate (CBR) format.
- When the buffer you are reenqueuing was allocated with the AudioQueueAllocateBufferWithPacketDescriptions (page 9) function. In this case, your callback should describe the buffer's packets in the buffer's mPacketDescriptions and mPacketDescriptionCount fields.

#### *inTrimFramesAtStart*

The number of priming frames to skip at the start of the buffer.

#### inTrimFramesAtEnd

The number of frames to skip at the end of the buffer.

### inNumParamValues

The number of audio queue parameter values pointed to by the inParamValues parameter. If you are not setting parameters, use 0.

#### inParamValues

An array of parameters to apply to an audio queue buffer. (In Mac OS X v10.5, there is only one audio queue parameter, kAudioQueueParam\_Volume.) If you are not setting parameters for the buffer, use NULL.

Assign parameter values before playback—they cannot be changed while a buffer is playing. Changes to audio queue buffer parameters take effect when the buffer starts playing.

#### inStartTime

The desired start time for playing the buffer. To specify a time relative to when the audio queue started, use the mSampleTime field of the AudioTimeStamp structure. Use NULL to indicate that the buffer should play as soon as possible—which may be after previously queued buffers finish playing.

Buffers play in the order they are enqueued (first in, first out). If multiple buffers are queued, the start times must be in ascending order or NULL; otherwise, an error occurs. This parameter specifies when audio data is to start playing, ignoring any trim frames specified in the <code>inTrimFramesAtStart</code> parameter.

### outActualStartTime

On output, the time when the buffer will actually start playing.

### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

You can exert some control over the buffer queue with this function. You can assign audio queue settings that are, in effect, carried by an audio queue buffer as you enqueue it. Hence, settings take effect when an audio queue buffer begins playing.

This function applies only to playback. Recording audio queues do not take parameters and do not support variable bit rate (VBR) formats (which might require trimming).

### **Availability**

Available in iOS 2.0 and later.

#### See Also

AudioQueueEnqueueBuffer (page 14)

#### **Declared In**

AudioQueue.h

### **AudioQueueFlush**

Resets an audio queue's decoder state.

```
OSStatus AudioQueueFlush (
    AudioQueueRef inAQ
):
```

#### **Parameters**

inAQ

The audio queue to flush.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

Call AudioQueueFlush after enqueuing the last audio queue buffer to ensure that all buffered data, as well as all audio data in the midst of processing, gets recorded or played. If you do not call this function, stale data in the audio queue's decoder may interfere with playback or recording of the next set of buffers.

Call this function before calling AudioQueueStop (page 30) if you want to ensure that all enqueued data reaches the destination. If you call AudioQueueStop with the <code>inImmediate</code> parameter set to <code>false</code>, calling this function does nothing; under those conditions, AudioQueueStop calls this function.

### **Availability**

Available in iOS 2.0 and later.

### See Also

```
AudioQueueDispose (page 13)
AudioQueueStop (page 30)
```

### **Related Sample Code**

**AOOfflineRenderTest** 

#### **Declared In**

AudioQueue.h

### **AudioQueueFreeBuffer**

Asks an audio queue to dispose of an audio queue buffer.

```
OSStatus AudioQueueFreeBuffer (
   AudioQueueRef inAQ,
   AudioQueueBufferRef inBuffer
);
```

### **Parameters**

inA0

The audio queue that owns the audio queue buffer you want to dispose of.

inBuffer

The buffer to dispose of.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

### Discussion

Disposing of an audio queue also disposes of its buffers. Call this function only if you want to dispose of a particular buffer while continuing to use an audio queue. You can dispose of a buffer only when the audio queue that owns it is stopped (that is, not processing audio data).

### **Availability**

Available in iOS 2.0 and later.

#### See Also

```
AudioQueueAllocateBuffer (page 8)
AudioQueueAllocateBufferWithPacketDescriptions (page 9)
AudioQueueDispose (page 13)
```

#### **Declared In**

AudioOueue.h

### AudioQueueGetCurrentTime

Gets the current audio queue time.

```
OSStatus AudioQueueGetCurrentTime (
   AudioQueueRef inAQ,
   AudioQueueTimelineRef inTimeline,
   AudioTimeStamp *outTimeStamp,
   Boolean *outTimelineDiscontinuity
);
```

### **Parameters**

inA0

The audio queue whose current time you want to get.

inTimeline

The audio queue timeline object to which timeline discontinuities are reported. Use NULL if the audio queue does not have an associated timeline object.

outTime

On output, the current audio queue time. The mSampleTime field represents audio queue time in terms of the audio queue sample rate, relative to when the queue started or will start.

```
outTimelineDiscontinuity
```

On output, true if there has been a timeline discontinuity, or false if there has been no discontinuity. If the audio queue does not have an associated timeline object, this parameter is always NULL.

A timeline discontinuity may occur, for example, if the sample rate is changed for the audio hardware device associated with an audio queue.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

### **Availability**

Available in iOS 2.0 and later.

#### See Also

```
AudioQueueCreateTimeline (page 10)
AudioQueueDeviceGetCurrentTime (page 11)
```

#### **Declared In**

AudioOueue.h

### **AudioQueueGetParameter**

Gets an audio queue parameter value.

```
OSStatus AudioQueueGetParameter (
AudioQueueRef inAQ,
AudioQueueParameterID inParamID,
AudioQueueParameterValue *outValue):
```

### **Parameters**

inAQ

The audio queue that you want to get a parameter value from.

inParamID

The ID of the parameter whose value you want to get. In Mac OS X v10.5, audio queues have one parameter available: kAudioQueueParam\_Volume, which controls playback gain. See "Audio Queue Parameter Identifiers" (page 40)

outValue

On output, points to the current value of the specified parameter.

### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

You can access the current parameter values for an audio queue at any time with this function. An audio queue parameter value is the sum of settings applied at buffer granularity, using the AudioQueueEnqueueBufferWithParameters (page 15) function, and settings applied to the audio queue per se, using the AudioQueueSetParameter (page 28) function.

#### Availability

Available in iOS 2.0 and later.

#### See Also

AudioQueueSetParameter (page 28)

### **Declared In**

AudioQueue.h

### AudioQueueGetProperty

Gets an audio queue property value.

```
OSStatus AudioQueueGetProperty (
   AudioQueueRef inAQ,
   AudioQueuePropertyID inID,
   void *outData,
   UInt32 *ioDataSize
):
```

### **Parameters**

inA0

The audio queue that you want to get a property value from.

inID

The ID of the property whose value you want to get. See "Audio Queue Property Identifiers" (page 38).

outData

On output, the desired property value.

ioDataSize

On input, the maximum bytes of space the caller expects to receive. On output, the actual data size of the property value.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

Before calling this function, you can use the AudioQueueGetPropertySize (page 21) function to determine the size, in bytes, of the value of a specified property. Some properties have values of a specific size, as described in "Audio Queue Property Identifiers" (page 38).

### **Availability**

Available in iOS 2.0 and later.

### See Also

```
AudioQueueSetProperty (page 28)
AudioQueueGetPropertySize (page 21)
```

### **Related Sample Code**

SpeakHere

### **Declared In**

AudioQueue.h

### AudioQueueGetPropertySize

Gets the size of the value of an audio queue property.

```
OSStatus AudioQueueGetPropertySize (
   AudioQueueRef inAQ,
   AudioQueuePropertyID inID,
   UInt32 *outDataSize
);
```

#### **Parameters**

inAQ

The audio queue that has the property value whose size you want to get.

inID

The ID of the property value whose size you want to get. See "Audio Queue Property Identifiers" (page 38).

outDataSize

On output, the size of the requested property value.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

### Availability

Available in iOS 2.0 and later.

#### See Also

AudioQueueGetProperty (page 20)

### **Related Sample Code**

SpeakHere

### **Declared In**

AudioQueue.h

### AudioQueueNewInput

Creates a new recording audio queue object.

### **Parameters**

inFormat

The compressed or uncompressed audio data format to record to. When recording to linear PCM, only interleaved formats are supported.

21

#### inCallbackProc

A callback function to use with the recording audio queue. The audio queue calls this function when the audio queue has finished filling a buffer. See AudioQueueInputCallback (page 31).

inUserData

A custom data structure for use with the callback function.

```
inCallbackRunLoop
```

The event loop on which the callback function pointed to by the inCallback Proc parameter is to be called. If you specify NULL, the callback is called on one of the audio queue's internal threads.

```
inCallbackRunLoopMode
```

The run loop mode in which to invoke the callback function specified in the inCallbackProc parameter. Typically, you pass kCFRunLoopCommonModes or use NULL, which is equivalent. You can choose to create your own thread with your own run loops. For more information on run loops, see Run Loops and CFRunLoop Reference.

inFlags

Reserved for future use. Must be 0.

out AO

On output, the newly created recording audio queue.

### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### **Availability**

Available in iOS 2.0 and later.

#### See Also

AudioQueueSetOfflineRenderFormat (page 27)

### **Related Sample Code**

SpeakHere

#### **Declared In**

AudioQueue.h

### AudioQueueNewOutput

Creates a new playback audio queue object.

```
OSStatus AudioQueueNewOutput (
   const AudioStreamBasicDescription *inFormat,
  AudioQueueOutputCallback
                                       inCallbackProc,
   void
                                        *inUserData,
  CFRunLoopRef
                                       inCallbackRunLoop,
  CFStringRef
                                        inCallbackRunLoopMode,
  UInt32
                                        inFlags,
   AudioOueueRef
                                        *outAQ
);
```

### **Parameters**

inFormat

The data format of the audio to play. For linear PCM, only interleaved formats are supported. Compressed formats are also supported.

22

#### inCallbackProc

A callback function to use with the playback audio queue. The audio queue invokes the callback when the audio queue has finished acquiring a buffer. See AudioQueueOutputCallback (page 32).

inUserData

A custom data structure for use with the callback function.

inCallbackRunLoop

The event loop on which the callback function pointed to by the inCallback Proc parameter is to be called. If you specify NULL, the callback is invoked on one of the audio queue's internal threads.

inCallbackRunLoopMode

The run loop mode in which to invoke the callback function specified in the inCallbackProc parameter. Typically, you pass kCFRunLoopCommonModes or use NULL, which is equivalent. You can choose to create your own thread with your own run loops. For more information on run loops, see Run Loops and CFRunLoop Reference.

inFlags

Reserved for future use. Must be 0.

out AO

On output, the newly created playback audio queue object.

### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### **Availability**

Available in iOS 2.0 and later.

#### See Also

AudioQueueOfflineRender (page 23)

### **Related Sample Code**

AOOfflineRenderTest

SpeakHere

### **Declared In**

AudioQueue.h

### AudioOueueOfflineRender

Exports audio to a buffer, instead of to a device, using a playback audio queue.

```
OSStatus AudioOueueOfflineRender (
  AudioQueueRef inAQ,
  const AudioTimeStamp *inTimestamp,
   AudioOueueBufferRef ioBuffer.
   UInt32 inNumberFrames
):
```

#### **Parameters**

inAQ

The playback audio queue.

The time corresponding to the beginning of the current audio queue buffer. This function uses the mSampleTime field of the AudioTimeStamp data structure.

23

ioBuffer

On input, a buffer you supply to hold rendered audio data. On output, the rendered audio data, which you can then write to a file.

inRequestedFrames

The number of frames of audio to render.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

When you change a playback audio queue's rendering mode to offline, using the AudioQueueSetOfflineRenderFormat (page 27) function, you gain access to the rendered audio. You can then write the audio to a file, rather than have it play to external hardware such as a loudspeaker.

### **Availability**

Available in iOS 2.0 and later.

#### See Also

```
AudioQueueSetOfflineRenderFormat (page 27)
AudioQueueStart (page 29)
```

### **Related Sample Code**

AQOfflineRenderTest

#### **Declared In**

AudioQueue.h

### **AudioQueuePause**

Pauses audio playback or recording.

```
OSStatus AudioQueuePause (
    AudioQueueRef inAQ
):
```

### **Parameters**

inA0

The audio queue to pause.

### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

Pausing an audio queue does not affect buffers or reset the audio queue. To resume playback or recording, call AudioQueueStart (page 29).

### Availability

Available in iOS 2.0 and later.

#### See Also

```
AudioQueueStart (page 29)
AudioQueueStop (page 30)
```

### **Related Sample Code**

SpeakHere

#### **Declared In**

AudioQueue.h

### **AudioQueuePrime**

Decodes enqueued buffers in preparation for playback.

```
OSStatus AudioQueuePrime (
   AudioQueueRef inAQ,
   UInt32 inNumberOfFramesToPrepare,
   UInt32 *outNumberOfFramesPrepared
):
```

#### **Parameters**

inAQ

The audio queue to be primed.

inNumberOfFramesToPrepare

The number of frames to decode before returning. Pass 0 to decode all enqueued buffers.

outNumberOfFramesPrepared

On output, the number of frames actually decoded and prepared for playback. Pass NULL on input if you you are not interested in this information.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

This function decodes enqueued buffers in preparation for playback. It returns when at least the number of audio sample frames specified in <code>inNumberOfFramesToPrepare</code> are decoded and ready to play, or (if you pass 0 for the <code>inNumberOfFramesToPrepare</code> parameter), when all enqueued buffers are decoded.

To make a buffer of audio data ready to play, use AudioQueuePrime as follows:

- 1. Call AudioQueueEnqueueBuffer (page 14).
- 2. Call AudioQueuePrime.
- 3. Call AudioQueueStart (page 29).

#### **Availability**

Available in iOS 2.0 and later.

### **Declared In**

AudioQueue.h

### AudioQueueRemovePropertyListener

Removes a property listener callback from an audio queue.

Functions

```
OSStatus AudioQueueRemovePropertyListener (
AudioQueueRef inAQ,
AudioQueuePropertyID inID,
AudioQueuePropertyListenerProc inProc,
void *inUserData
);
```

#### **Parameters**

inA0

The audio queue that you want to remove a property listener callback from.

inID

The ID of the property whose changes you no longer want to respond to. See "Audio Queue Property Identifiers" (page 38).

inProc

The callback to be removed.

inUserData

The same custom data for the property listener callback that you passed when calling AudioQueueAddPropertyListener (page 8).

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

### **Availability**

Available in iOS 2.0 and later.

#### See Also

AudioQueueAddPropertyListener (page 8)

#### **Declared In**

AudioQueue.h

### **AudioQueueReset**

Resets an audio queue.

```
OSStatus AudioQueueReset (
    AudioQueueRef inAQ
);
```

#### **Parameters**

inAQ

The audio queue to reset.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

### Discussion

This function immediately resets an audio queue, flushes any queued buffers (invoking callbacks as necessary), removes all buffers from previously scheduled use, and resets decoder and digital signal processing (DSP) state.

If you queue buffers after calling this function, processing does not begin until the decoder and DSP state of the audio queue are reset. This might create an audible discontinuity (or "glitch").

This function is called automatically when you call AudioQueueStop (page 30).

### **Availability**

Available in iOS 2.0 and later.

#### See Also

```
AudioQueuePause (page 24)
AudioQueueStop (page 30)
```

#### **Declared In**

AudioOueue.h

### AudioQueueSetOfflineRenderFormat

Sets the rendering mode and audio format for a playback audio queue.

```
OSStatus AudioQueueSetOfflineRenderFormat (
    AudioQueueRef inAQ,
    const AudioStreamBasicDescription *inFormat,
    const AudioChannelLayout *inLayout
);
```

#### **Parameters**

inA0

The playback audio queue whose rendering mode and audio format you want to set.

inFormat

The audio format for offline rendering. The format must be some sort of linear PCM. If the format has more than one channel, it must be interleaved. For more information on the

 ${\tt AudioStreamBasicDescription} \ \textit{structure, see} \ \textit{Core} \ \textit{Audio} \ \textit{Data} \ \textit{Types} \ \textit{Reference.}$ 

Pass NULL to disable offline rendering and return the audio queue to normal output to an audio device.

inLayout

The channel layout for offline rendering. For more information on the AudioChannel Layout structure, see Core Audio Data Types Reference.

Pass NULL when using this function to disable offline rendering.

### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

Use this function to set a playback audio queue to perform offline rendering, such as for export to an audio file. In offline rendering mode, a playback audio queue does not connect to external hardware.

You can also use this function to restore an audio queue to normal rendering mode by passing NULL in the inFormat and inLayout parameters.

#### **Availability**

Available in iOS 2.0 and later.

#### See Also

AudioQueueOfflineRender (page 23)

### **Related Sample Code**

AQOfflineRenderTest

#### **Declared In**

AudioQueue.h

### AudioQueueSetParameter

Sets a playback audio queue parameter value.

```
OSStatus AudioQueueSetParameter (
AudioQueueRef inAQ,
AudioQueueParameterID inParamID,
AudioQueueParameterValue inValue);
```

### **Parameters**

inA0

The playback audio queue that you want to set a parameter value on.

inParamID

The ID of the parameter you want to set. In Mac OS X v10.5, audio queues have one parameter available: kAudioQueueParam\_Volume, which controls playback gain. See "Audio Queue Parameter Identifiers" (page 40).

inValue

The parameter value to set.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

Use this function to change the settings for a playback audio queue directly. Changes take effect immediately. To set playback gain at the granularity of an audio queue buffer, use the

AudioQueueEnqueueBufferWithParameters (page 15) function.

#### **Availability**

Available in iOS 2.0 and later.

#### See Also

```
AudioQueueGetParameter (page 19)
AudioQueueEngueueBufferWithParameters (page 15)
```

### **Related Sample Code**

SpeakHere

### **Declared In**

AudioQueue.h

### AudioQueueSetProperty

Sets an audio queue property value.

```
OSStatus AudioQueueSetProperty (
   AudioQueueRef inAQ,
   AudioQueuePropertyID inID,
   const void *inData,
   UInt32 inDataSize
);
```

#### **Parameters**

inA0

The audio queue that you want to set a property value on.

inID

The ID of the property whose value you want to set. See "Audio Queue Property Identifiers" (page 38).

inData

The property value to set.

inDataSize

The size of the property data.

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

### **Availability**

Available in iOS 2.0 and later.

#### See Also

AudioQueueGetProperty (page 20)

#### **Related Sample Code**

AQOfflineRenderTest

SpeakHere

#### **Declared In**

AudioOueue.h

### AudioQueueStart

Begins playing or recording audio.

```
OSStatus AudioQueueStart (
   AudioQueueRef inAQ,
   const AudioTimeStamp *inStartTime
);
```

### **Parameters**

inA0

The audio queue to start.

inDeviceStartTime

The time at which the audio queue should start.

To specify a start time relative to the timeline of the associated audio device, use the mSampleTime field of the AudioTimeStamp structure. Use NULL to indicate that the audio queue should start as soon as possible.

29

Functions

#### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

If the associated audio device is not already running, this function starts it.

### **Availability**

Available in iOS 2.0 and later.

#### See Also

```
AudioQueueStop (page 30)
AudioQueuePause (page 24)
```

### **Related Sample Code**

AQOfflineRenderTest

SpeakHere

#### **Declared In**

AudioQueue.h

### AudioQueueStop

Stops playing or recording audio.

```
OSStatus AudioQueueStop (
   AudioQueueRef inAQ,
   Boolean inImmediate
);
```

#### **Parameters**

inAQ

The audio queue to stop.

inImmediate

If you pass true, stopping occurs immediately (that is, *synchronously*). If you pass false, the function returns immediately, but the audio queue does not stop until its queued buffers are played or recorded (that is, the stop occurs *asynchronously*). Audio queue callbacks are invoked as necessary until the queue actually stops.

### **Return Value**

A result code. See "Audio Queue Result Codes" (page 42).

#### Discussion

This function resets an audio queue, stops the audio hardware associated with the queue if it is not in use by other audio services, and stops the audio queue. When recording, this function is typically invoked by a user. When playing back, a playback audio queue callback should call this function when there is no more audio to play.

### **Availability**

Available in iOS 2.0 and later.

### See Also

```
AudioQueueStart (page 29)
AudioQueueReset (page 26)
AudioQueuePause (page 24)
```

### Related Sample Code AQOfflineRenderTest

SpeakHere

#### **Declared In**

AudioOueue.h

## Callbacks by Task

## Handling Audio Queue Buffers for Recording and Playback

```
AudioQueueInputCallback (page 31)
```

Called by the system when a recording audio queue has finished filling an audio queue buffer.

AudioQueueOutputCallback (page 32)

Called by the system when an audio queue buffer is available for reuse.

## **Defining a Property Listener**

```
AudioQueuePropertyListenerProc (page 33)
```

Called by the system when a specified audio queue property changes value.

## **Callbacks**

### AudioQueueInputCallback

Called by the system when a recording audio queue has finished filling an audio queue buffer.

If you name your callback function MyAudioQueueInputCallback, you would declare it like this:

#### **Parameters**

inUserData

The custom data you've specified in the inUserData parameter of the AudioQueueNewInput (page 21) function. Typically, this includes format and state information for the audio queue.

inAQ

The recording audio queue that invoked the callback.

inBuffer

An audio queue buffer, newly filled by the recording audio queue, containing the new audio data your callback needs to write.

inStartTime

The sample time for the start of the audio queue buffer. This parameter is not used in basic recording. inNumberPacketDescriptions

The number of packets of audio data sent to the callback in the *inBuffer* parameter. When recording in a constant bit rate (CBR) format, the audio queue sets this parameter to NULL.

inPacketDescs

For compressed formats that require packet descriptions, the set of packet descriptions produced by the encoder for audio data in the inBuffer parameter. When recording in a CBR format, the audio queue sets this parameter to NULL.

#### Discussion

You specify a recording audio queue callback when calling the AudioQueueNewInput (page 21) function. The callback is invoked each time its recording audio queue has filled an audio queue buffer with fresh audio data. Typically, your callback writes the data to a file or other buffer, and then reenqueues the audio queue buffer to receive more data.

### **Availability**

Available in iOS 2.0 and later.

### Declared In

AudioQueue.h

### AudioQueueOutputCallback

Called by the system when an audio queue buffer is available for reuse.

If you name your callback function MyAudioQueueOutputCallback, you would declare it like this:

):

#### **Parameters**

inUserData

The custom data you've specified in the inUserData parameter of the AudioQueueNewOutput (page 22) function. Typically, this includes data format and state information for the audio queue.

inA0

The playback audio queue that invoked the callback.

inBuffer

An audio queue buffer, newly available to fill because the playback audio queue has acquired its contents.

#### Discussion

This callback function is invoked each time its associated playback audio queue has acquired the data from an audio queue buffer, at which point the buffer is available for reuse. The newly-available buffer is sent to this callback in the <code>inBuffer</code> parameter. Typically, you write this callback to:

- 1. Fill the newly-available buffer with the next set of audio data from a file or other buffer.
- 2. Reenqueue the buffer for playback. To reenqueue a buffer, use the AudioQueueEnqueueBuffer (page 14) or AudioQueueEnqueueBufferWithParameters (page 15) function.

To associate this callback with a playback audio queue, provide a reference to the callback as you are creating the audio queue. See the <code>inCallbackProc</code> parameter of the AudioQueueNewOutput (page 22) function.

When the system invokes this callback, you cannot assume that the audio data from the newly-available buffer has been played. For a description of how to check that a sound has finished playing, read the Discussion for the AudioQueuePropertyListenerProc (page 33) callback function.

#### **Availability**

Available in iOS 2.0 and later.

#### Declared In

AudioQueue.h

### Audio Queue Property Listener Proc

Called by the system when a specified audio queue property changes value.

If you name your callback function MyAudioQueuePropertyListenerProc, you would declare it like this:

Callbacks

#### **Parameters**

inUserData

The custom data you've specified in the inUserData parameter of the AudioQueueAddPropertyListener (page 8) function.

inAQ

The recording or playback audio queue that invoked the callback.

inID

The ID of the property whose value changes you want to observe.

#### Discussion

Install this callback in an audio queue by calling the AudioQueueAddPropertyListener (page 8) function. For example, say you want your application to be notified, after you call the AudioQueueStop (page 30) function with the inImmedate parameter set to false, that audio has finished playing. Perform these steps:

- 1. Define this property listener callback function to listen for changes to the kAudioQueueProperty\_IsRunning (page 38) property.
- 2. Install this callback, using the AudioQueueAddPropertyListener (page 8) function, in the playback audio queue that you want to monitor.

#### **Availability**

Available in iOS 2.0 and later.

#### Declared In

AudioQueue.h

## **Data Types**

### **AudioQueueBuffer**

Defines an audio queue buffer.

```
typedef struct AudioQueueBuffer {
   const UInt32
                                mAudioDataBytesCapacity:
   void
                                *const mAudioData;
   UInt32
                                mAudioDataBvteSize:
   void
                                *mUserData:
   const UInt32
                                mPacketDescriptionCapacity;
   AudioStreamPacketDescription *const mPacketDescriptions;
                                 mPacketDescriptionCount;
   UInt32
} AudioOueueBuffer:
typedef AudioQueueBuffer *AudioQueueBufferRef;
```

### Fields

mAudioDataBytesCapacity

The size of the audio queue buffer, in bytes. This size is set when an buffer is allocated and cannot be changed.

mAudioData

The audio data owned the audio queue buffer. The buffer address cannot be changed.

mAudioDataByteSize

The number of bytes of valid audio data in the audio queue buffer's mAudioData field, initially set to 0. Your callback must this value for a playback audio queue; for recording, the recording audio queue sets the value.

mUserData

The custom data structure you specify, for use by your callback function, when creating a recording or playback audio queue.

mPacketDescriptionCapacity

 $\label{thm:canbe} \textbf{The maximum number of packet descriptions that can be stored in the \verb|mPacketDescriptions| field.} \\ \text{mPacketDescriptions}$ 

An array of AudioStreamPacketDescription structures for the buffer.

mPacketDescriptionCount

The number of valid packet descriptions in the buffer. You set this value when providing buffers for playback. The audio queue sets this value when returning buffers from a recording queue.

#### Discussion

Each audio queue has an associated set of audio queue buffers. To allocate a buffer, call the AudioQueueAllocateBuffer (page 8) function. To dispose of a buffer, call the AudioQueueFreeBuffer (page 18) function.

If using a VBR compressed audio data format, you may want to instead use the

AudioQueueAllocateBufferWithPacketDescriptions function. This function allocates a buffer with additional space for packet descriptions. The mPacketDescriptionCapacity, mPacketDescriptions, and mPacketDescriptionCount fields may only be used with buffers allocated with AudioQueueAllocateBufferWithPacketDescriptions.

### **Availability**

Available in iOS 2.0 and later.

### **Declared In**

AudioQueue.h

### **AudioQueueBufferRef**

A pointer to an audio queue buffer.

typedef AudioQueueBuffer \*AudioQueueBufferRef;

### Availability

Available in iOS 2.0 and later.

#### **Declared In**

AudioOueue.h

### AudioQueueRef

Defines an opaque data type that represents an audio queue.

typedef struct OpaqueAudioQueue \*AudioQueueRef;

### Discussion

An audio queue is a software object you use for recording or playing audio in Mac OS X. It does the work of:

Data Types
2011-01-03 | © 2011 Apple Inc. All Rights Reserved.

- Connecting to audio hardware
- Managing memory
- Employing codecs, as needed, for compressed audio formats
- Mediating recording or playback

You create, use, and dispose of audio queues using the functions described in "Audio Queue Functions" (page 8).

### **Availability**

Available in iOS 2.0 and later.

#### **Declared In**

AudioQueue.h

### AudioQueueTimelineRef

Defines an opaque data type that represents an audio queue timeline object.

```
typedef struct OpaqueAudioQueueTimeline *AudioQueueTimelineRef;
```

### Discussion

You can use a timeline object to observe time discontinuities in the audio hardware device associated with an audio queue. A discontinuity is, for example, a period of silence when sound was expected. Causes of discontinuities include changes in device state or data processing overloads. See Technical Q&A 1467, CoreAudio Overload Warnings. You query a timeline object by passing it as a parameter to the AudioQueueGetCurrentTime (page 18) function.

### **Availability**

Available in iOS 2.0 and later.

### **Declared In**

AudioQueue.h

### AudioQueueLevelMeterState

Specifies the current level metering information for one channel of an audio queue..

```
typedef struct AudioQueueLevelMeterState {
    Float32     mAveragePower;
    Float32     mPeakPower;
}; AudioQueueLevelMeterState;
```

#### **Fields**

mAveragePower

The audio channel's average RMS power.

mPeakPower

The audio channel's peak RMS power.

### **Availability**

Available in iOS 2.0 and later.

#### **Declared In**

AudioQueue.h

### AudioQueueParameterEvent

Specifies an audio queue parameter and associated value.

```
struct AudioQueueParameterEvent {
   AudioQueueParameterID     mID;
   AudioQueueParameterValue    mValue;
}; typedef struct AudioQueueParameterEvent AudioQueueParameterEvent;
```

#### **Fields**

mΙD

The parameter.

mValue

The value of the specified parameter.

#### Discussion

You use this structure with the AudioQueueEnqueueBufferWithParameters (page 15) function. See that function, and "Audio Queue Parameter Identifiers" (page 40), for more information.

### **Availability**

Available in iOS 2.0 and later.

### **Declared In**

AudioQueue.h

### AudioQueueParameterID

A UInt32 value that uniquely identifies an audio queue parameter.

```
typedef UInt32 AudioQueueParameterID;
```

#### **Availability**

Available in iOS 2.0 and later.

### **Declared In**

AudioQueue.h

### AudioQueueParameterValue

A Float32 value for an audio queue parameter.

typedef Float32 AudioQueueParameterValue;

### **Availability**

Available in iOS 2.0 and later.

### **Declared In**

AudioQueue.h

### **Constants**

## **Audio Queue Property Identifiers**

Identifiers for audio queue properties.

```
enum {
                                              = 'aqrn',
   kAudioQueueProperty_IsRunning
   kAudioQueueDeviceProperty_SampleRate = 'agsr'
   kAudioQueueDeviceProperty_NumberChannels
                                              = 'aqdc'
   kAudioQueueProperty_CurrentDevice
                                              = 'aqcd',
                                              = 'agmc',
   kAudioQueueProperty_MagicCookie
   kAudioQueueProperty_MaximumOutputPacketSize = 'xops',
   kAudioQueueProperty_StreamDescription = 'aqft',
   kAudioQueueProperty_ChannelLayout
                                              = 'agcl',
   kAudioQueueProperty_EnableLevelMetering = 'agme',
   kAudioQueueProperty_CurrentLevelMeter
                                            = 'aqmv',
   kAudioQueueProperty_CurrentLevelMeterDB = 'agmd',
   kAudioQueueProperty_DecodeBufferSizeFrames = 'dcbf'
};
typedef UInt32 AudioQueuePropertyID;
```

### **Constants**

kAudioQueueProperty\_IsRunning

A read-only property whose value is a UInt32. Any nonzero value means running, and 0 means stopped. A notification is sent when the associated audio queue starts or stops, which may occur sometime after the AudioQueueStart (page 29) or AudioQueueStop (page 30) function is called.

Available in iOS 2.0 and later.

Declared in AudioQueue.h.

kAudioQueueDeviceProperty\_SampleRate

A read-only property whose value is a Float64. The value is the sampling rate of the audio hardware device associated with an audio queue.

Available in iOS 2.0 and later.

Declared in AudioQueue.h.

kAudioQueueDeviceProperty\_NumberChannels

A read-only property whose value is a UIInt32. The value is the number of channels in the audio hardware device associated with an audio queue.

Available in iOS 2.0 and later.

Declared in AudioQueue.h.

kAudioQueueProperty\_CurrentDevice

A read-write property whose value is of type CFStringRef. The value contains the unique identifier (UID) of the audio hardware device associated with an audio queue.

Available in iOS 2.0 and later.

Declared in AudioQueue.h.

### kAudioQueueProperty\_MagicCookie

A read-write property whose value is a void pointer to a block of memory, which you set up, containing an audio format magic cookie. If the audio format you are playing or recording to requires a magic cookie, you must set a value for this property before enqueuing any buffers.

Available in iOS 2.0 and later.

Declared in AudioOueue.h.

### kAudioQueueProperty\_MaximumOutputPacketSize

A read-only property whose value is a UInt32. The value is the size, in bytes, of the largest single packet of data in the output format. Primarily useful when encoding VBR compressed data.

Available in iOS 2.0 and later.

Declared in AudioQueue.h.

#### kAudioQueueProperty\_StreamDescription

A read-only property whose value is an AudioStreamBasicDescription structure, indicating an audio queue's data format. Primarily useful for obtaining a complete ASBD when recording, in cases where you initially specify a sample rate of 0.

Available in iOS 2.0 and later.

Declared in AudioQueue.h.

### kAudioQueueProperty\_ChannelLayout

A read-write property whose value is an AudioChannelLayout structure that describes an audio queue channel layout. The number of channels in the layout must match the number of channels in the audio format. This property is typically not used in the case of one or two channel audio. For more than two channels (such as in the case of 5.1 surround sound), you may need to specify a channel layout to indicate channel order, such as left, then center, then right.

Available in iOS 2.0 and later.

Declared in AudioQueue.h.

### kAudioQueueProperty\_EnableLevelMetering

A read-write property whose value is a UInt32 that indicates whether audio level metering is enabled for an audio queue. 0 =metering off, 1 =metering on.

Available in iOS 2.0 and later.

Declared in AudioQueue.h.

### kAudioQueueProperty\_CurrentLevelMeter

A read-only property whose value is an array of AudioQueueLevelMeterState (page 36) structures, one array element per audio channel. The member values in the structure are in the range 0 (for silence) to 1 (indicating maximum level).

Available in iOS 2.0 and later.

Declared in AudioQueue.h.

### kAudioQueueProperty\_CurrentLevelMeterDB

A read-only property whose value is an array of AudioQueueLevelMeterState (page 36) structures, one array element per audio channel. The member values in the structure are in decibels.

Available in iOS 2.0 and later.

Declared in AudioOueue.h.

Constants 39

kAudioQueueProperty\_DecodeBufferSizeFrames

A read-write property whose value is a UInt32 that is the size of the buffer into which a playback (output) audio queue decodes buffers. A larger buffer provides more reliability and better long-term performance at the expense of memory and decreased responsiveness in some situations.

Available in iOS 2.0 and later.

Declared in AudioOueue.h.

#### Discussion

To receive a notification that a specific audio queue property has changed:

- 1. Define a property listener callback, referencing the desired audio queue property ID. Base the callback on the AudioQueuePropertyListenerProc (page 33) callback function declaration.
- 2. Assign the callback to an audio queue using the AudioQueueAddPropertyListener (page 8) function.
- 3. When you get a property-changed notification, call the AudioQueueGetProperty (page 20) function to get the current value of the property.

#### Declared In

AudioQueue.h

### **Audio Queue Parameters**

Identifiers for audio queue parameters.

#### Constants

kAudioQueueParam\_Volume

The linearly scaled gain for the audio queue, in the range 0.0 through 1.0. A value of 1.0 (the default) indicates unity gain. A value of 0.0 indicates zero gain, or silence.

Available in iOS 2.0 and later.

Declared in AudioQueue.h.

kAudioQueueParam\_VolumeRampTime

The number of seconds over which a volume change is ramped.

For example, to fade from unity gain down to silence over the course of 1 second, set this parameter to 1 and then set the  $kAudioQueueParam\_Volume$  parameter to 0.

Available in iOS 4.0 and later.

Declared in AudioOueue.h.

kAudioQueueParam\_Pan

The stereo panning position of a source. For a monophonic source, panning is determined as follows:

- −1 = hard left
- 0 = center
- +1 = hard right

For a stereophonic source, this parameter affects the left/right balance. For a multichannel source, this parameter has no effect.

Available in iOS 4.0 and later.

Declared in AudioQueue.h.

#### Discussion

These parameters apply only to playback audio queues. You can set a playback audio queue parameter in one of two ways:

- Set the value to take effect immediately using the AudioQueueSetParameter (page 28) function.
- Schedule a value to take effect when a particular audio queue buffer plays. You supply the parameter
  when you enqueue the buffer. The new value is applied to the audio queue that owns the buffer when
  that buffer is rendered.

The AudioQueueGetParameter (page 19) function always returns the current value of the parameter for an audio queue.

### **Declared In**

AudioQueue.h

## **Hardware Codec Policy Keys**

Indicates how an audio queue should choose between hardware and software implementations of a codec.

#### **Constants**

kAudioQueueProperty\_HardwareCodecPolicy

The preferred codec implementation type—hardware or software—for an audio queue. Possible values for this constant are the remaining constants described in this section.

Available in iOS 3.0 and later.

Declared in AudioQueue.h.

### kAudioQueueHardwareCodecPolicy\_Default

If the required codec is available in both hardware and software implementations, the audio queue will use a hardware codec if its audio session category permits; it will use a software codec otherwise. If the required codec is available in only one form, that codec implementation is used.

Available in iOS 3.0 and later.

Declared in AudioOueue.h.

### kAudioQueueHardwareCodecPolicy\_UseSoftwareOnly

The audio queue will use a software codec if one is available.

Available in iOS 3.0 and later.

Declared in AudioOueue.h.

#### kAudioQueueHardwareCodecPolicy\_UseHardwareOnly

The audio queue will use a hardware codec if one is available and if its use is permitted by the audio session category that you have set.

Available in iOS 3.0 and later.

Declared in AudioOueue.h.

#### kAudioQueueHardwareCodecPolicy\_PreferSoftware

The audio queue will use a software codec if one is available; if not, it will use a hardware codec if one is available and if its use is permitted by the audio session category that you have set.

Available in iOS 3.0 and later.

Declared in AudioQueue.h.

### kAudioQueueHardwareCodecPolicy\_PreferHardware

The audio queue will use a hardware codec if one is available and if its use permitted by the audio session category that you have set; otherwise, it will use a software codec if one is available.

Available in iOS 3.0 and later.

Declared in AudioQueue.h.

#### Discussion

If the designated codec implementation is not available, or if a hardware codec is chosen and the audio session category does not permit use of hardware codecs, your attempts to call the AudioQueuePrime (page 25) or AudioQueueStart (page 29) functions will fail.

Use the kAudioFormatProperty\_Encoders or kAudioFormatProperty\_Decoders properties to determine whether the codec you are interested in using is available in hardware form, software, or both. See the discussion for kAudioFormatProperty\_HardwareCodecCapabilities.

### The system does not permit you to change the value associated with the

kAudioQueueProperty\_HardwareCodecPolicy key while the audio queue is primed or running. Changing the value at other times may cause codec settings to be lost.

## **Result Codes**

This table lists result codes defined for Audio Queue Services.

Result Code	Value	Description
kAudioQueueErr_InvalidBuffer	-66687	The specified audio queue buffer does not belong to the specified audio queue.
		Available in iOS 2.0 and later.
kAudioQueueErr_BufferEmpty	-66686	The audio queue buffer is empty (that is, the mAudioDataByteSize field = 0).
		Available in iOS 2.0 and later.
kAudioQueueErr_DisposalPending	-66685	The function cannot act on the audio queue because it is being asynchronously disposed of.
		Available in iOS 2.0 and later.
kAudioQueueErr_InvalidProperty	-66684	The specified property ID is invalid.
		Available in iOS 2.0 and later.
kAudioQueueErr_InvalidPropertySize	-66683	The size of the specified property is invalid.
		Available in iOS 2.0 and later.
kAudioQueueErr_InvalidParameter	-66682	The specified parameter ID is invalid.
		Available in iOS 2.0 and later.
kAudioQueueErr_CannotStart	-66681	The audio queue has encountered a problem and cannot start.
		Available in iOS 2.0 and later.
kAudioQueueErr_InvalidDevice	-66680	The specified audio hardware device could not be located.
		Available in iOS 2.0 and later.
kAudioQueueErr_BufferInQueue	-66679	The audio queue buffer cannot be disposed of when it is enqueued.
		Available in iOS 2.0 and later.
kAudioQueueErr_InvalidRunState	-66678	The queue is running but the function can only operate on the queue when it is stopped, or vice versa.
		Available in iOS 2.0 and later.
kAudioQueueErr_InvalidQueueType	-66677	The queue is an input queue but the function can
		only operate on an output queue, or vice versa.
		Available in iOS 2.0 and later.
kAudioQueueErr_Permissions	-66676	You do not have the required permissions to call the function.
		Available in iOS 2.0 and later.

Result Code	Value	Description
kAudioQueueErr_InvalidPropertyValue	-66675	The property value used is not valid.
		Available in iOS 2.0 and later.
kAudioQueueErr_PrimeTimedOut	-66674	During a call to the AudioQueuePrime (page 25) function, the audio queue's audio converter failed to convert the requested number of sample frames.
		Available in iOS 2.2 and later.
kAudioQueueErr_CodecNotFound	-66673	The requested codec was not found.
		Available in iOS 3.0 and later.
kAudioQueueErr_InvalidCodecAccess	-66672	The codec could not be accessed.
		Available in iOS 3.0 and later.
kAudioQueueErr_QueueInvalidated	-66671	In iPhone OS, the audio server has exited, causing the audio queue to become invalid.
		Available in iOS 3.0 and later.
kAudioQueueErr_EnqueueDuringReset	-66632	During a call to the AudioQueueReset (page 26), AudioQueueStop (page 30), or AudioQueueDispose (page 13) functions, the system does not allow you to enqueue buffers.
		Available in iOS 3.0 and later.
kAudioQueueErr_InvalidOfflineMode	-66626	The operation requires the audio queue to be in offline mode but it isn't, or vice versa.
		To use offline mode or to return to normal mode, use the AudioQueueSetOfflineRenderFormat (page 27) function.
		Available in iOS 3.1 and later.
kAudioFormatUnsupportedDataFormatError	1718449215 = 'fmt?'	The playback data format is unsupported (declared in AudioFormat.h).
		Available in iOS 2.0 and later.

# **Document Revision History**

This table describes the changes to Audio Queue Services Reference.

Date	Notes	
2011-01-03	Added descriptions for new audio queue playback parameters in "Audio Queue Parameters" (page 40).	
2010-02-01	Corrected description for the inCallbackProc parameter in the AudioQueueNewOutput (page 22) function.	
	Improved discussion for the AudioQueueOutputCallback (page 32) callback function.	
2009-08-07	Added description for "kAudioQueueErr_InvalidOfflineMode" (page 44) result code.	
2009-06-19	Added description for AudioQueueBufferRef (page 35) type definition.	
2009-03-29	Updated for iPhone OS 3.0.	
	Added descriptions for new result codes:  "kAudioQueueErr_QueueInvalidated" (page 44) and  "kAudioQueueErr_EnqueueDuringReset" (page 44). Added descriptions for constants that support the use of hardware codecs: "Hardware Codec Policy Keys" (page 41).	
2008-11-12	Added description for new "kAudioQueueErr_PrimeTimedOut" (page 44) result code.	
2008-07-08	Updated for platform-specific support.	
2008-01-15	Corrected and clarified descriptions of the AudioQueueOutputCallback (page 32) and AudioQueuePropertyListenerProc (page 33) callback functions.	
2007-10-31	New document that describes a high-level programming interface for playing and recording audio data.	

### **REVISION HISTORY**

**Document Revision History**