

ClamAV Bytecode Compiler

User Manual

Contents

1	Inst	Installation 1				
	1.1	Requirements				
	1.2	Obtaining the ClamAV Bytecode Compiler				
	1.3	Building				
		1.3.1 Disk space				
		1.3.2 Create build directory				
	1.4	Testing				
	1.5	Installing				
		1.5.1 Structure of installed files				
2	Tut	orial 5				
	2.1	Short introduction to the bytecode language				
		2.1.1 Types, variables and constants				
		2.1.2 Arrays and pointers				
		2.1.3 Arithmetics				
		2.1.4 Functions				
		2.1.5 Control flow				
		2.1.6 Common functions				
	2.2	Writing logical signatures				
		2.2.1 Structure of a bytecode for algorithmic detection				
		2.2.2 Virusnames				
		2.2.3 Patterns				
		2.2.4 Single subsignature				
		2.2.5 Multiple subsignatures				
		2.2.6 W32.Polipos.A detector rewritten as bytecode				
		2.2.7 Virut detector in bytecode				
	2.3	Writing regular expressions in bytecode				
		2.3.1 A very simple regular expression				
		2.3.2 Named regular expressions				
	2.4	Writing unpackers				
		2.4.1 Structure of a bytecode for unpacking (and other hooks)				
		2.4.2 Detecting clam.exe via bytecode				
		2.4.3 Detecting clam.exe via bytecode (disasm)				
		2.4.4 A simple unpacker				
		2.4.5 Matching PDF javascript				
		2.4.6 YC unpacker rewritten as bytecode				
3	Usa	nge				

ii		Cor	ntents
	3.1	Invoking the compiler	15
		3.1.1 Compiling C++ files	15
	3.2	Running compiled bytecode	15
		3.2.1 ClamBC	16
		3.2.2 clamscan, clamd	16
	3.3	Debugging bytecode	16
		3.3.1 "printf" style debugging	16
		3.3.2 Single-stepping	17
4	Cla	nAV bytecode language	19
	4.1	Differences from C99 and GNU C	19
	4.2	Limitations	20
	4.3	Logical signatures	21
	4.4	Headers and runtime environment	23
5	Byt	ecode security & portability	25
		·	
6	Rep	orting bugs	27
7		ecode API	29
	7.1	API groups	29
		7.1.1 Bytecode configuration	29
		7.1.2 Data structure handling functions	30
		7.1.3 Disassemble APIs	31
		7.1.4 Engine queries	32
		7.1.5 Environment detection functions	32
		7.1.6 File operations	33
		7.1.7 Global variables	33
		7.1.8 Icon matcher APIs	33
		7.1.9 JS normalize API	34
		7.1.10 Math functions	34
		7.1.11 PDF handling functions	34
		7.1.13 Scan control functions	35 38
		7.1.14 String operations	38
	7.2	Structure types	39
	1.2	7.2.1 cli exe info Struct Reference	39
		7.2.1.1 Detailed Description	39
		7.2.1.2 Field Documentation	39
		7.2.2 cli exe section Struct Reference	39
		7.2.2.1 Detailed Description	40
		7.2.2.2 Field Documentation	40
		7.2.3 cli_pe_hook_data Struct Reference	40
		7.2.3.1 Detailed Description	41
		7.2.3.2 Field Documentation	41
		7.2.4 DIS_arg Struct Reference	41
		7.2.4 Dis_arg better reference	41
		7.2.4.2 Field Documentation	42
		7.2.5 DIS fixed Struct Reference	42
		7 2 5 1 Detailed Description	42

Contents								
			7.2.5.2 Field Documentation	42				
		7.2.6	DIS_mem_arg Struct Reference					
			7.2.6.1 Detailed Description					
			7.2.6.2 Field Documentation					
		7.2.7	DISASM_RESULT Struct Reference	43				
			7.2.7.1 Detailed Description	43				
		7.2.8	pe_image_data_dir Struct Reference					
			7.2.8.1 Detailed Description	43				
		7.2.9	pe_image_file_hdr Struct Reference	43				
			7.2.9.1 Detailed Description	44				
			7.2.9.2 Field Documentation	44				
		7.2.10	pe_image_optional_hdr32 Struct Reference	44				
			7.2.10.1 Detailed Description	45				
			7.2.10.2 Field Documentation	45				
		7.2.11	pe_image_optional_hdr64 Struct Reference	45				
			7.2.11.1 Detailed Description	46				
			7.2.11.2 Field Documentation	46				
		7.2.12	pe_image_section_hdr Struct Reference	47				
			7.2.12.1 Detailed Description					
			7.2.12.2 Field Documentation	47				
	7.3	Low le	evel API	47				
		7.3.1	bytecode_api.h File Reference	47				
			7.3.1.1 Detailed Description					
			7.3.1.2 Enumeration Type Documentation					
			7.3.1.3 Function Documentation	51				
			7.3.1.4 Variable Documentation					
		7.3.2	bytecode_disasm.h File Reference					
			7.3.2.1 Detailed Description					
			7.3.2.2 Enumeration Type Documentation					
		7.3.3	bytecode_execs.h File Reference					
			7.3.3.1 Detailed Description					
		7.3.4	bytecode_pe.h File Reference	83				
		1 1	7.3.4.1 Detailed Description					
	7.4		evel API					
		7.4.1	bytecode_local.h File Reference					
			7.4.1.1 Detailed Description					
			7.4.1.2 Define Documentation					
			7.4.1.3 Function Documentation	89				
8	Copyright and License							
	8.1		SlamAV Bytecode Compiler	105				
	8.2		ode	107				
\mathbf{A}	\mathbf{Pre}	define	d macros	109				

Contents

ClamAV Bytecode Compiler - Internals Manual,

© 2009 Sourcefire, Inc.

Authors: Török Edvin

This document is distributed under the terms of the GNU General Public License v2.

Clam AntiVirus is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; version 2 of the License.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.

ClamAV and Clam AntiVirus are trademarks of Sourcefire, Inc.

CHAPTER 1 Installation

1.1. Requirements

The ClamAV Bytecode Compiler uses the LLVM compiler framework, thus requires an Operating System where building LLVM is supported:

- FreeBSD/x86
- $Linux/\{x86,x86_64,ppc\}$
- Mac OS $X/\{x86,ppc\}$
- Solaris/sparcv9
- Windows/x86 using mingw32 or Visual Studio

The following packages are required to compile the ClamAV Bytecode Compiler:

- GCC C and C++ compilers (minimum 4.1.3, recommended: 4.3.4 or newer) ¹.
- Perl (version 5.6.0+)
- GNU make (version 3.79+, recommended 3.81)

The following packages are optional, but highly recommended:

• Python (version 2.5.4+?) - for running the tests

1.2. Obtaining the ClamAV Bytecode Compiler

You can obtain the source code in one of the following ways 2

- Check out the source code using git native protocol: git clone git://git.clamav.net/git/clamav-bytecode-compiler
- Check out the source code using HTTP:

```
git clone http://git.clamav.net/git/clamav-bytecode-compiler.git
```

You can keep the source code updated using:

git pull

¹Note that several versions of GCC have bugs when compiling LLVM, see http://llvm.org/docs/GettingStarted.html#brokengcc for a full list. Also LLVM requires support for atomic builtins for multithreaded mode, which gcc 3.4.x doesn't have

 $^{^2} For now the use the internal clamtools repository: git clone username@git.clam.sourcefire.com:/var/lib/git/clamtools.git$

2 1.3. Building

1.3. Building

1.3.1. Disk space

A minimalistic release build requires 100M of disk space.

Testing the compiler requires a full build, 320M of disk space. A debug build requires significantly more disk space (1.4G for a minimalistic debug build).

Note that this only needed during the build process, once installed only 12M is needed.

1.3.2. Create build directory

Building requires a separate object directory, building in the source directory is not supported. Create a build directory:

```
$ cd clamav-bytecode-compiler && mkdir obj
Run configure (you can use any prefix you want, this example uses /usr/local/clamav):
$ cd obj && ../llvm/configure --enable-optimized \
    --enable-targets=host-only --disable-bindings \
    --prefix=/usr/local/clamav
Run the build under ulimit ¹:
$ (ulimit -t 3600 -v 512000 && make clambc-only -j4)
```

1.4. Testing

```
$ (ulimit -t 3600 v 512000 && make -j4)
$ make check-all
```

If make check reports errors, check that your compiler is NOT on this list: http://llvm.org/docs/GettingStarted.html#brokengcc.

If it is, then your compiler is buggy, and you need to do one of the following: upgrade your compiler to a non-buggy version, upgrade the OS to one that has a non-buggy compiler, compile with export OPTMIZE_OPTION=-02, or export OPTIMIZE_OPTION=-01, or export OPTIMIZE_OPTION=\-01.

If not you probably found a bug, report it at http://bugs.clamav.net

1.5. Installing

Install it:

```
$ make install-clambc -j8
```

¹compiling some files can be very memory intensive, especially with older compilers

Chapter 1. Installation

1.5.1. Structure of installed files

- 1. The ClamAV Bytecode compiler driver: \$PREFIX/bin/clambc-compiler
- 2. ClamAV bytecode header files:

```
$PREFIX/lib/clang/1.1/include:
bcfeatures.h
bytecode_{api_decl.c,api,disasm,execs,features}.h
bytecode.h
bytecode_{local,pe,types}.h
```

 $3.\,$ clang compiler (with ClamAV by tecode backend) compiler include files:

```
$PREFIX/lib/clang/1.1/include:
emmintrin.h
float.h
iso646.h
limits.h
{,p,t,x}mmintrin.h
mm_malloc.h
std{arg,bool,def,int}.h
tgmath.h
```

4. User manual

\$PREFIX/docs/clamav/clambc-user.pdf

4 1.5. Installing

CHAPTER 2 Tutorial

2.1. Short introduction to the bytecode language

- **2.1.1.** Types, variables and constants
- **2.1.2.** Arrays and pointers
- 2.1.3. Arithmetics
- **2.1.4.** Functions
- **2.1.5.** Control flow
- **2.1.6.** Common functions

2.2. Writing logical signature bytecodes

¹ Logical signatures can be used as triggers for executing bytecode. However, instead of describing a logical signature as a .ldb pattern, you use (simple) C code which is later translated to a .ldb-style logical signature by the ClamAV Bytecode Compiler.

A bytecode triggered by a logical signature is much more powerful than a logical signature itself: you can write complex algorithmic detections, and use the logical signature as a *filter* (to speed up matching). Thus another name for "logical signature bytecodes" is "algorithmic detection bytecodes". The detection you write in bytecode has read-only access to the file being scanned and its metadata (PE sections, EP, etc.).

2.2.1. Structure of a bytecode for algorithmic detection

Algorithmic detection bytecodes are triggered when a logical signature matches. They can execute an algorithm that determines whether the file is infected and with which virus.

A bytecode can be either algorithmic or an unpacker (or other hook), but not both. It consists of:

• Definition of virusnames used in the bytecode

 $^{^1\}mathrm{See}$ Section 4.3 for more details about logical signatures in bytecode.

- Pattern definitions (for logical subexpressions)
- The logical signature as C function: bool logical_trigger(void)
- The int entrypoint(void) function which gets executed when the logical signature matches
- (Optional) Other functions and global constants used in entrypoint

The syntax for defining logical signatures, and an example is described in Section 2.2.4. The function entrypoint must report the detected virus by calling foundVirus and returning 0. It is recommended that you always return 0, otherwise a warning is shown and the file is considered clean. If foundVirus is not called, then ClamAV also assumes the file is clean.

2.2.2. Virusnames

Each logical signature bytecode must have a virusname prefix, and one or more virusnames. The virusname prefix is used by the SI to ensure unique virusnames (a unique number is appended for duplicate prefixes).

Program 1 Declaring virusnames

```
1 /* Prefix, used for duplicate detection and fixing */
VIRUSNAME_PREFIX("Trojan.Foo")
3 /* You are only allowed to set these virusnames as found */
VIRUSNAMES("A", "B")
5 /* File type */
TARGET(2)
```

In Program 1 3 predefied macros are used:

- VIRUSNAME_PREFIX which must have exactly one string argument
- VIRUSNAMES which must have one or more string arguments
- TARGET which must have exactly one integer argument

In this example, the bytecode could generate one of these virusnames: Trojan.Foo.A, or Trojan.Foo.B, by calling foundVirus("A") or foundVirus("B") respectively (notice that the prefix is not part of these calls).

2.2.3. Patterns

Logical signatures use .ndb style patterns, an example on how to define these is shown in Program 2.

Each pattern has a name (like a variable), and a string that is the hex pattern itself. The declarations are delimited by the macros SIGNATURES_DECL_BEGIN, and SIGNATURES_DECL_END. The definitions are delimited by the macros SIGNATURES_DEF_BEGIN, and SIGNATURES_END. Declarations must always come before definitions, and you can have only one declaration and declaration section! (think of declaration like variable declarations, and definitions as variable assignments, since that what they are under the hood). The order in which you declare the signatures is the order in which they appear in the generated logical signature.

Chapter 2. Tutorial 7

Program 2 Declaring patterns

```
SIGNATURES_DECL_BEGIN

DECLARE_SIGNATURE (magic)
DECLARE_SIGNATURE (check)

DECLARE_SIGNATURE (zero)
SIGNATURES_DECL_END

SIGNATURES_DEF_BEGIN
DEFINE_SIGNATURE (magic, "EP+0:aabb")
DEFINE_SIGNATURE (check, "f00d")
DEFINE_SIGNATURE (zero, "fffff")
SIGNATURES_END
```

You can use any name for the patterns that is a valid record field name in C, and doesn't conflict with anything else declared.

After using the above macros, the global variable Signatures will have two new fields: magic, and zero. These can be used as arguments to the functions count_match(), and matches() anywhere in the program as shown in Program 3:

- matches(Signatures.match) will return true when the match signature matches (at least once)
- count_match(Signatures.zero) will return the number of times the zero signature matched
- count_match(Signatures.check) will return the number of times the check signature matched

The condition in the if can be interpreted as: if the match signature has matched at least once, and the number of times the zero signature matched is higher than the number of times the check signature matched, then we have found a virus A, otherwise the file is clean.

Program 3 Using patterns

```
int entrypoint(void)
{
   if (matches(Signatures.match) && count_match(Signatures.zero) >
        count_match(Signatures.check))
      foundVirus("A");
   return 0;
}
```

2.2.4. Single subsignature

The simplest logical signature is like a .ndb signature: a virus name, signature target, 0 as logical expression 1 , and a ndb-style pattern.

The code for this is shown in Program 4

The logical signature (created by the compiler) looks like this: Trojan.Foo.{A}; Target:2;0;aabb

 $^{^{1}}$ meaning that subexpression 0 must match

Program 4 Single subsignature example

```
/* Declare the prefix of the virusname */
<sup>'</sup>2 VIRUSNAME_PREFIX("Trojan.Foo")
  /* Declare the suffix of the virusname */
4 VIRUSNAMES ("A")
  /* Declare the signature target type (1 = PE) */
6 TARGET (1)
8 /* Declare the name of all subsignatures used */
  SIGNATURES_DECL_BEGIN
10 DECLARE_SIGNATURE(magic)
  SIGNATURES_DECL_END
/* Define the pattern for each subsignature */ ^{\rm 14} SIGNATURES_DEF_BEGIN
  DEFINE_SIGNATURE(magic, "aabb")
16 SIGNATURES_END
18 /* All bytecode triggered by logical signatures must have this
     function */
20 bool logical_trigger(void)
    /* return true if the magic subsignature matched,
22
     * its pattern is defined above to "aabb" */
    return count_match(Signatures.magic) != 2;
  }
26
  /* This is the bytecode function that is actually executed when the logical
   * signature matched */
  int entrypoint(void)
30 {
    /st call this function to set the suffix of the virus found st/
   foundVirus("A");
    /* success, return 0 */
34
    return 0;
```

Chapter 2. Tutorial

Of course you should use a .ldb signature in this case when all the processing in entrypoint is only setting a virusname and returning. However, you can do more complex checks in entrypoint, once the bytecode was triggered by the logical_trigger

In the example in Program 4 the pattern was used without an anchor; such a pattern matches at any offset. You can use offsets though, the same way as in .ndb signatures, see Program 5 for an example.

2.2.5. Multiple subsignatures

An example for this is shown in Program 5. Here you see the following new features used: 1

- Multiple virusnames returned from a single bytecode (with common prefix)
- Multiple subsignatures, each with a name of your choice
- A pattern with an anchor (EP+0:aabb)
- More subsignatures defined than used in the logical expression

The logical signature looks like this:

 $Trojan.Foo.\{A,B\}; Target:2; (((0|1|2)=42,2)|(3=10)); EP+0: aabb; fffff; aaccee; f00d; dead$

Notice how the subsignature that is not used in the logical expression (number 4, dead) is used in entrypoint to decide the virus name. This works because ClamAV does collect the match counts for all subsignatures (regardless if they are used or not in a signature). The count_match(Signatures.check2) call is thus a simple memory read of the count already determined by ClamAV.

Also notice that comments can be used freely: they are ignored by the compiler. You can use either C-style multiline comments (start comment with /*, end with */), or C++-style single-line comments (start comment with //, automatically ended by newline).

2.2.6. W32.Polipos.A detector rewritten as bytecode

2.2.7. Virut detector in bytecode

2.3. Writing regular expressions in bytecode

ClamAV only supports a limited set of regular expressions in .ndb format: wildcards. The bytecode compiler allows you to compile fully generic regular expressions to bytecode directly. When libclamav loads the bytecode, it will compile to native code (if using the JIT), so it should offer quite good performance.

The compiler currently uses re2c to compile regular expressions to C code, and then compile that to bytecode. The internal workings are all transparent to the user: the compiler automatically uses re2c when needed, and re2c is embedded in the compiler, so you don't need to install it.

The syntax of regular expressions are similar to the one used by POSIX regular expressions, except you have to quote literals, since unquoted they are interpreted as regular expression names.

¹In case of a duplicate virusname the prefix is appended a unique number by the SI

Program 5 Multiple subsignatures

```
1 /* You are only allowed to set these virusnames as found */
  VIRUSNAME_PREFIX("Test")
3 VIRUSNAMES ("A", "B")
  TARGET (1)
  SIGNATURES_DECL_BEGIN
7 DECLARE_SIGNATURE(magic)
  DECLARE_SIGNATURE(zero)
9 DECLARE_SIGNATURE(check)
  DECLARE_SIGNATURE(fivetoten)
11 DECLARE_SIGNATURE(check2)
  SIGNATURES_DECL_END
  SIGNATURES_DEF_BEGIN
15 DEFINE_SIGNATURE(magic, "EP+0:aabb")
DEFINE_SIGNATURE(zero, "fffff")
17 DEFINE_SIGNATURE(fivetoten, "aaccee")
DEFINE_SIGNATURE(check, "f00d")
19 DEFINE_SIGNATURE(check2, "dead")
  SIGNATURES_END
21
  bool logical_trigger(void)
23 {
      unsigned sum_matches = count_match(Signatures.magic)+
           count_match(Signatures.zero) + count_match(Signatures.fivetoten);
25
       unsigned unique_matches = matches(Signatures.magic)+
27
               matches(Signatures.zero)+ matches(Signatures.fivetoten);
       if (sum_matches == 42 && unique_matches == 2) {
           // The above 3 signatures have matched a total of 42 times, and at least
29
           // 2 of them have matched
           return true;
31
      }
      // If the check signature matches 10 times we still have a match
33
       if (count_match(Signatures.check) == 10)
           return true;
35
       // No match
      return false;
37
  }
39
  int entrypoint(void)
41 {
      unsigned count = count_match(Signatures.check2);
43
      if (count >= 2)
           foundVirus(count = 2 ? "A" : "B");
  //
         if (count == 2)
45
           foundVirus("A");
         else
47
           foundVirus("B");
      return 0;
49
  }
```

Chapter 2. Tutorial

2.3.1. A very simple regular expression

Lets start with a simple example, to match this POSIX regular expression: eval($[a-zA-Z_]$ [$a-zA-Z0-9_]*$ \.unescape. See Program 6 ¹.

Program 6 Simple regular expression example

```
int entrypoint(void)
       REGEX_SCANNER;
       seek(0, SEEK_SET);
       for (;;) {
           REGEX_LOOP_BEGIN
6
           /* !re2c
              ANY = [\hat{}];
10
               "eval("[a-zA-Z_][a-zA-Z_0-9]*".unescape" {
                  long pos = REGEX_POS;
12
                  if (pos < 0)
                    continue;
14
                  debug("unescape found at:");
                  debug (pos);
16
              ANY
                   { continue; }
18
20
       return 0;
22 }
```

There are several new features introduced here, here is a step by step breakdown:

REGEX_SCANNER this declares the data structures needed by the regular expression matcher

- seek(0, SEEK_SET) this sets the current file offset to position 0, matching will start at this position. For offset 0 it is not strictly necessary to do this, but it serves as a reminder that you might want to start matching somewhere, that is not necessarily 0.
- for(;;) { REGEX_LOOP_BEGIN this creates the regular expression matcher main loop. It takes the current file byte-by-byte 2 and tries to match one of the regular expressions.
- /*!re2c This mark the beginning of the regular expression description. The entire regular expression block is a C comment, starting with !re2c
- ANY = [^]; This declares a regular expression named ANY that matches any byte.
- "eval("[a-zA-Z_] [a-zA-Z_0-9]*".unescape" { This is the actual regular expression.
 - "eval(" This matches the literal string eval(. Literals have to be placed in double quotes " here, unlike in POSIX regular expressions or PCRE. If you want case-insensitive matching, you can use '.
 - [a-zA-Z_] This is a character class, it matches any lowercase, uppercase or _ characters.

¹This omits the virusname, and logical signature declarations

²it is not really reading byte-by-byte, it is using a buffer to speed things up

12 2.4. Writing unpackers

[a-zA-Z_0-9]*" Same as before, but with repetition. * means match zero or more times, + means match one or more times, just like in POSIX regular expressions.

- ".unescape" A literal string again
- { start of the *action* block for this regular expression. Whenever the regular expression matches, the attached C code is executed.
- long pos = REGEX_POS; this determines the absolute file offset where the regular expression
 has matched. Note that because the regular expression matcher uses a buffer, using just
 seek(0, SEEK_CUR) would give the current position of the end of that buffer, and not the
 current position during regular expression matching. You have to use the REGEX_POS macro
 to get the correct position.
- debug(...) Shows a debug message about what was found and where. This is extremely helpful when you start writing regular expressions, and nothing works: you can determine whether your regular expression matched at all, and if it matched where you thought it would. There is also a DEBUG_PRINT_MATCH that prints the entire matched string to the debug output. Of course before publishing the bytecode you might want to turn off these debug messages.
- } closes the action block for this regular expression
- ANY { continue; } If none of the regular expressions matched so far, just keep running the matcher, at the next byte
- */ closes the regular expression description block
- } closes the for() loop

You may have multiple regular expressions, or declare multiple regular expressions with a name, and use those names to build more complex regular expressions.

2.3.2. Named regular expressions

2.4. Writing unpackers

2.4.1. Structure of a bytecode for unpacking (and other hooks)

When writing an unpacker, the bytecode should consist of:

- Define which hook you use (for example PE_UNPACKER_DECLARE for a PE hook)
- An int entrypoint (void) function that reads the current file and unpacks it to a new file
- Return 0 from entrypoint if you want the unpacked file to be scanned
- (Optional) Other functions and global constants used by entrypoint

2.4.2. Detecting clam.exe via bytecode

Example provided by aCaB:

Chapter 2. Tutorial	13
2.4.3. Detecting clam.exe via bytecode (disasm)	
Example provided by aCaB:	
2.4.4. A simple unpacker	
2.4.5. Matching PDF javascript	
2.4.6. YC unpacker rewritten as bytecode	

14 2.4. Writing unpackers

CHAPTER 3

Usage

3.1. Invoking the compiler

Compiling is similar to gcc ¹:

\$ /usr/local/clamav/bin/clambc-compiler foo.c -o foo.cbc -02

This will compile the file foo.c into a file called foo.cbc, that can be loaded by ClamAV, and packed inside a .cvd file.

The compiler by default has all warnings turned on.

Supported optimization levels: -00, -01, -02, -03. 2 It is recommended that you always compile with at least -01.

Warning options: -Werror (transforms all warnings into errors).

Preprocessor flags:

- -I <directory> Searches in the given directory when it encounters a #include "headerfile" directive in the source code, in addition to the system defined header search directories.
- -D <MACRONAME>=<VALUE> Predefine given <MACRONAME> to be equal to <VALUE>.
- -U <MACRONAME> Undefine a predefined macro

The compiler also supports some other commandline options (see clambc-compiler --help for a full list), however some of them have no effect when using the ClamAV bytecode backend (such as the X86 backend options). You shouldn't need to use any flags not documented above.

3.1.1. Compiling C++ files

Filenames with a .cpp extension are compiled as C++ files, however clang++ is not yet ready for production use, so this is EXPERIMENTAL currently. For now write bytecodes in C.

3.2. Running compiled bytecode

After compiling a C source file to bytecode, you can load it in ClamAV:

 $^{^{1}}$ Note that the ClamAV by tecode compiler will refuse to compile code it considers in secure

 $^{^2\}mathrm{Currently}$ -O0 doesn't work

3.2.1. ClamBC

ClamBC is a tool you can use to test whether the bytecode loads, compiles, and can execute its entrypoint successfully. Usage:

```
clambc <file> [function] [param1 ...]
```

For example loading a simple bytecode with 2 functions is done like this:

```
$ clambc foo.cbc
LibClamAV debug: searching for unrar, user-searchpath: /usr/local/lib
LibClamAV debug: unrar support loaded from libclamunrar_iface.so.6.0.4 libclamunrar_iface_so_u
LibClamAV debug: bytecode: Parsed 0 APIcalls, maxapi 0
LibClamAV debug: Parsed 1 BBs, 2 instructions
LibClamAV debug: Parsed 1 BBs, 2 instructions
LibClamAV debug: Parsed 2 functions
Bytecode loaded
Running bytecode function :0
Bytecode run finished
```

3.2.2. clamscan, clamd

Bytecode returned: 0x8

Exiting

You can tell clamscan to load the bytecode as a database directly:

```
$ clamscan -dfoo.cbc
```

Or you can instruct it to load all databases from a directory, then clamscan will load all supported formats, including files with bytecode, which have the .cbc extension.

```
$ clamscan -ddirectory
```

You can also put the bytecode files into the default database directory of ClamAV (usually /usr/local/share/clamav) to have it loaded automatically from there. Of course, the bytecode can be stored inside CVD files, too.

3.3. Debugging bytecode

3.3.1. "printf" style debugging

Printf, and printf-like format specifiers are not supported in the bytecode. You can use these functions instead of printf to print strings and integer to clamscan's –debug output:

```
debug_print_str, debug_print_uint, debug_print_str_start, debug_print_str_nonl.
```

You can also use the debug convenience wrapper that automatically prints as string or integer depending on parameter type: debug, debug, debug.

See Program 7 for an example.

Chapter 3. Usage

Program 7 Example of using debug APIs

```
/* test debug APIs */
  int entrypoint(void)
  {
3
    /* print a debug message, followed by newline */
    debug_print_str("bytecode started", 16);
    /* start a new debug message, don't end with newline yet */
    debug_print_str_start("Engine functionality level: ", 28);
    /* print an integer, no newline */
    debug_print_uint(engine_functionality_level());
    /\ast print a string without starting a new debug message, and without
11
     * terminating with newline */
    debug_print_str_nonl(", dconf functionality level: ", 28);
13
    debug_print_uint(engine_dconf_level());
    debug_print_str_nonl("\n", 1);
15
    debug_print_str_start("Engine scan options: ", 21);
    debug_print_uint(engine_scan_options());
    debug_print_str_nonl(", db options: ", 13);
    debug_print_uint(engine_db_options());
19
    debug_print_str_nonl("\n", 1);
21
    /* convenience wrapper to just print a string */
    debug("just print a string");
23
    /* convenience wrapper to just print an integer */
    debug(4);
    return OxfOOd;
27 }
```

3.3.2. Single-stepping

If you have GDB 7.0 (or newer) you can single-step ^{1 2} during the execution of the bytecode.

• Run clambe or clamscan under gdb:

```
$ ./libtool --mode=execute gdb clamscan/clamscan
...
(gdb) b cli_vm_execute_jit
Are you sure ....? y
(gdb) run -dfoo.cbc
...
Breakpoint ....
(gdb) step
(gdb) next
```

You can single-step through the execution of the bytecode, however you can't (yet) print values of individual variables, you'll need to add debug statements in the bytecode to print interesting values.

¹not yet implemented in libclamav

 $^{^2{\}rm assuming}$ you have JIT support

3.3. Debugging bytecode

CHAPTER 4

ClamAV bytecode language

The bytecode that ClamAV loads is a simplified form of the LLVM Intermediate Representation, and as such it is language-independent.

However currently the only supported language from which such by tecode can be generated is a simplified form of C $^{\rm 1}$

The language supported by the ClamAV bytecode compiler is a restricted set of C99 with some GNU extensions.

4.1. Differences from C99 and GNU C

These restrictions are enforced at compile time:

- No standard include files. ²
- The ClamAV API header files are preincluded.
- No external function calls, except to the ClamAV API ³
- No inline assembly ⁴
- Globals can only be readonly constants ⁵
- inline is C99 inline (equivalent to GNU C89 extern inline), thus it cannot be used outside of the definition of the ClamAV API, you should use static inline
- sizeof(int) == 4 always
- sizeof(long) == sizeof(long long) == 8 always
- ptr_diff_t = int, intptr_t = int, intmax_t = long, uintmax_t = unsigned long 6
- No pointer to integer casts and integer to pointer casts (pointer arithmetic is allowed though)

¹In the future more languages could be supported, see the Internals Manual on language frontends

 $^{^2\}mathrm{For}$ portability reasons: preprocessed C code is not portable

 $^{^3}$ For safety reasons we can't allow the bytecode to call arbitrary system functions

⁴This is both for safety and portability reasons

 $^{^5 \}mathrm{For}$ thread safety reasons

⁶Note that a pointer's size of is runtime-platform dependent, although at compile time size of (void*) == 4, at runtime it can be something else. Thus you should avoid using size of (pointer)

20 4.2. Limitations

- No __thread support
- Size of memory region associated with each pointer must be known in each function, thus if you pass a pointer to a function, you must also pass its allocated size as a parameter.
- Endianness must be handled via the __is_bigendian() API function call, or via the cli_{read,write}int{16,32} wrappers, and not by casting pointers
- Predefines __CLAMBC__
- All integer types have fixed width
- main or entrypoint must have the following prototype: int main(void), the prototype int main(int argc, char *argv[]) is not accepted

They are meant to ensure the following:

- Thread safe execution of multiple different bytecodes, and multiple instances of the same bytecode
- Portability to multiple CPU architectures and OSes: the bytecode must execute on both the libclamav/LLVM JIT where that is supported (x86, x86_64, ppc, arm?), and on the libclamav interpreter where that is not supported.
- No external runtime dependency: libclamav should have everything needed to run the bytecode, thus no external calls are allowed, not even to libc!
- Same behaviour on all platforms: fixed size integers.

These restrictions are checked at runtime (checks are inserted at compile time):

- Accessing an out-of-bounds pointer will result in a call to abort()
- Calling abort() interrupts the execution of the bytecode in a thread safe manner, and doesn't halt ClamAV ¹.

The ClamAV API header has further restriction, see the Internals manual.

Although the bytecode undergoes a series of automated tests (see Publishing chapter in Internals manual), the above restrictions don't guarantee that the resulting bytecode will execute correctly! You must still test the code yourself, these restrictions only avoid the most common errors. Although the compiler and verifier aims to accept only code that won't crash ClamAV, no code is 100% perfect, and a bug in the verifier could allow unsafe code be executed by ClamAV.

4.2. Limitations

The bytecode format has the following limitations:

- At most 64k bytecode kinds (hooks)
- At most 64k types (including pointers, and all nested types)
- At most 16 parameters to functions, no vararg functions

¹in fact it calls a ClamAV API function, and not the libc abort function.

- At most 64-bit integers
- No vector types or vector operations
- No opaque types
- No floating point
- Global variable initializer must be compile-time computable
- At most 32k global variables (and at most 32k API globals)
- Pointer indexing at most 15 levels deep (can be worked around if needed by using temporaries)
- No struct return or byval parameters
- At most 32k instructions in a single function
- No Variable Length Arrays

4.3. Logical signatures

Logical signatures can be used as triggers for executing a bytecode. Instead of describing a logical signatures as a .1db pattern, you use C code which is then translated to a .1db-style logical signature.

Logical signatures in ClamAV support the following operations:

- Sum the count of logical subsignatures that matched inside a subexpression
- Sum the number of different subsignatures that matched inside a subexpression
- Compare the above counts using the >,=,< relation operators
- Perform logical &&, || operations on above boolean values
- Nest subexpressions
- Maximum 64 subexpressions

Out of the above operations the ClamAV Bytecode Compiler doesn't support computing sums of nested subexpressions, (it does support nesting though).

The C code that can be converted into a logical signature must obey these restrictions:

- a function named logical_trigger with the following prototype: bool logical_trigger(void)
- no function calls, except for count_match and matches
- no global variable access (except as done by the above 2 functions internally)
- return true when signature should trigger, false otherwise
- use only integer compare instructions, branches, integer add, logical and, logical or, logical xor, zero extension, store/load from local variables

4.3. Logical signatures

• the final boolean expression must be convertible to disjunctive normal form without negation

- the final logical expression must not have more than 64 subexpressions
- it can have early returns (all true returns are unified using ||)
- · you can freely use comments, they are ignored
- the final boolean expression cannot be a true or false constant

The compiler does the following transformations (not necessarily in this order):

- convert shortcircuit boolean operations into non-shortcircuit ones (since all operands are boolean expressions or local variables, it is safe to execute these unconditionally)
- propagate constants
- simplify control flow graph
- (sparse) conditional constant propagation
- dead store elimination
- dead code elimination
- instruction combining (arithmetic simplifications)
- jump threading

If after this transformation the program meets the requirements outlined above, then it is converted to a logical signature. The resulting logical signature is simplified using basic properties of boolean operations, such as associativity, distributivity, De Morgan's law.

The final logical signature is not unique (there might be another logical signature with identical behavior), however the boolean part is in a canonical form: it is in disjunctive normal form, with operands sorted in ascending order.

For best results the C code should consist of:

- local variables declaring the sums you want to use
- a series of if branches that return true, where the if's condition is a single comparison
 or a logical and of comparisons
- a final return false

You can use || in the if condition too, but be careful that after expanding to disjunctive normal form, the number of subexpressions doesn't exceed 64.

Note that you do not have to use all the subsignatures you declared in logical_trigger, you can do more complicated checks (that wouldn't obey the above restrictions) in the bytecode itself at runtime. The logical_trigger function is fully compiled into a logical signature, it won't be a runtime executed function (hence the restrictions).

4.4. Headers and runtime environment

When compiling a bytecode program, bytecode.h is automatically included, so you don't need to explicitly include it. These headers (and the compiler itself) predefine certain macros, see Appendix A for a full list. In addition the following types are defined:

```
typedef unsigned char uint8_t;
2 typedef char int8_t;
typedef unsigned short uint16_t;
4 typedef short int16_t;
typedef unsigned int uint32_t;
6 typedef int int32_t;
typedef unsigned long uint64_t;
8 typedef long int64_t;
typedef unsigned int size_t;
10 typedef int off_t;
typedef struct signature { unsigned id } __Signature;
```

As described in Section 4.1 the width of integer types are fixed, the above typedefs show that.

A bytecode's entrypoint is the function entrypoint and it's required by ClamAV to load the bytecode.

Bytecode that is triggered by a logical signature must have a list of virus names and patterns defined. Bytecodes triggered via hooks can optionally have them, but for example a PE unpacker doesn't need virus names as it only processes the data.

CHAPTER 5 Bytecode security & portability

CHAPTER 6 Reporting bugs

CHAPTER 7 Bytecode API

7.1. API groups

7.1.1. Bytecode configuration

Global COPYRIGHT(c) This will also prevent the sourcecode from being embedded into the bytecode

Global DECLARE_SIGNATURE(name)

Global DEFINE_SIGNATURE(name, hex)

Global FUNCTIONALITY_LEVEL_MAX(m)

Global FUNCTIONALITY_LEVEL_MIN(m)

Global ICONGROUP1(group)

Global ICONGROUP2(group)

Global PDF_HOOK_DECLARE This hook is called several times, use pdf_get_phase() to find out in which phase you got called.

Global PE_HOOK_DECLARE

Global PE_UNPACKER_DECLARE

Global SIGNATURES_DECL_BEGIN

Global SIGNATURES_DECL_END

Global SIGNATURES_DEF_BEGIN

Global SIGNATURES_END

Global TARGET(tgt)

Global VIRUSNAME_PREFIX(name)

Global VIRUSNAMES(...)

7.1. API groups

7.1.2. Data structure handling functions

Global buffer_pipe_done(int32_t id) After this all attempts to use this buffer will result in error. All buffer_pipes are automatically deallocated when bytecode finishes execution. Global buffer_pipe_new(uint32_t size) Global buffer_pipe_new_fromfile(uint32_t pos) Global buffer_pipe_read_avail(int32_t id) Global buffer pipe read get(int32 t id, uint32 t amount) The 'amount' parameter should be obtained by a call to buffer_pipe_read_avail(). Global buffer_pipe_read_stopped(int32_t id, uint32_t amount) Updates read cursor in buffer pipe. Global buffer_pipe_write_avail(int32_t id) Global buffer_pipe_write_get(int32_t id, uint32_t size) Returns pointer to writable buffer. The 'amount' parameter should be obtained by a call to buffer_pipe_write_avail(). Global buffer_pipe_write_stopped(int32_t id, uint32_t amount) Global cli readint16(const void *buff) Global cli_readint32(const void *buff) Global cli_writeint32(void *offset, uint32_t v) Global hashset_add(int32_t hs, uint32_t key) Global hashset_contains(int32_t hs, uint32_t key) Global hashset_done(int32_t id) Trying to use the hashset after this will result in an error. The hashset may not be used after this. All hashsets are automatically deallocated when bytecode finishes execution. Global hashset_empty(int32_t id) Global hashset_new(void)

```
Global hashset_remove(int32_t hs, uint32_t key)
Global inflate_done(int32_t id)
Global inflate_init(int32_t from_buffer, int32_t to_buffer, int32_t windowBits)
    'from buffer' and writing uncompressed uncompressed data 'to buffer'.
Global inflate_process(int32_t id)
Global le16_to_host(uint16_t v)
Global le32_to_host(uint32_t v)
Global le64_to_host(uint64_t v)
Global malloc(uint32_t size)
Global map_addkey(const uint8_t *key, int32_t ksize, int32_t id)
Global map_done(int32_t id)
Global map_find(const uint8_t *key, int32_t ksize, int32_t id)
Global map_getvalue(int32_t id, int32_t size)
Global map_getvaluesize(int32_t id)
Global map_new(int32_t keysize, int32_t valuesize)
Global map_remove(const uint8_t *key, int32_t ksize, int32_t id)
Global map_setvalue(const uint8_t *value, int32_t vsize, int32_t id)
7.1.3. Disassemble APIs
Class DIS_arg
Class DIS fixed
Class DIS_mem_arg
Global disasm_x86(struct DISASM_RESULT *result, uint32_t len)
Global DisassembleAt(struct DIS_fixed *result, uint32_t offset, uint32_t len)
```

32 7.1. API groups

7.1.4. Engine queries

```
Global count_match(___Signature sig)
Global engine_db_options(void)
Global engine_dconf_level(void)
Global engine_functionality_level(void)
Global engine_scan_options(void)
Global match_location(___Signature sig, uint32_t goback)
Global match_location_check(___Signature sig, uint32_t goback, const char *static_start, uint3
    It is recommended to use this for safety and compatibility with 0.96.1
Global matches(___Signature sig)
7.1.5. Environment detection functions
Global ___is_bigendian(void) ___attribute___((const )) ___attribute___((nothrow))
Global check_platform(uint32_t a, uint32_t b, uint32_t c)
Global disable_bytecode_if(const int8_t *reason, uint32_t len, uint32_t cond)
Global disable_jit_if(const int8_t *reason, uint32_t len, uint32_t cond)
Global get_environment(struct cli_environment *env, uint32_t len)
Global version_compare(const uint8_t *lhs, uint32_t lhs_len, const uint8_t *rhs, uint32_t rhs_
```

Chapter 7. Bytecode API 33

7.1.6. File operations

Global buffer_pipe_new_fromfile(uint32_t pos) to the current file, at the specified position.

Global file_byteat(uint32_t offset)

Global file_find(const uint8_t *data, uint32_t len)

Global file_find_limit(const uint8_t *data, uint32_t len, int32_t maxpos)

Global fill_buffer(uint8_t *buffer, uint32_t len, uint32_t filled, uint32_t cursor, uint32_t fill)

Global getFilesize(void)

Global read(uint8_t *data, int32_t size)

Global read_number(uint32_t radix) Non-numeric characters are ignored.

Global seek(int32_t pos, uint32_t whence)

Global write(uint8_t *data, int32_t size)

7.1.7. Global variables

Global ___clambc_filesize[1]

Global ___clambc_kind

Global ___clambc_match_counts[64]

Global ___clambc_match_offsets[64]

Global ___clambc_pedata

7.1.8. Icon matcher APIs

Global matchicon(const uint8_t *group1, int32_t group1_len, const uint8_t *group2, int32_t group2_

7.1. API groups

7.1.9. JS normalize API

```
Global jsnorm_done(int32_t id)
```

Global jsnorm_init(int32_t from_buffer)

Global jsnorm_process(int32_t id)

7.1.10. Math functions

```
Global icos(int32_t a, int32_t b, int32_t c)
```

```
Global iexp(int32_t a, int32_t b, int32_t c)
```

```
Global ilog2(uint32_t a, uint32_t b)
```

Global ipow(int32_t a, int32_t b, int32_t c)

Global isin(int32_t a, int32_t b, int32_t c)

7.1.11. PDF handling functions

Global pdf_get_dumpedobjid(void) Valid only in PDF_PHASE_POSTDUMP.

Global pdf_get_flags(void)

Global pdf_get_obj_num(void)

Global pdf_get_phase(void) Identifies at which phase this bytecode was called.

Global pdf_getobj(int32_t objidx, uint32_t amount) Meant only for reading, write modifies the fmap buffer, so avoid!

Global pdf_getobjsize(int32_t objidx)

Global pdf_lookupobj(uint32_t id)

Global pdf_set_flags(int32_t flags)

7.1.12. PE functions

```
Class\ cli\_exe\_info
{\bf Class\ cli\_exe\_section}
Class cli_pe_hook_data
Global get_pe_section(struct cli_exe_section *section, uint32_t num)
Global getEntryPoint(void)
Global \ getExeOffset(void)
Global getImageBase(void)
Global getNumberOfSections(void)
Global getPEBaseOfCode(void)
Global getPEBaseOfData(void)
Global getPECharacteristics()
Global getPECheckSum(void)
Global getPEDataDirRVA(unsigned n)
Global getPEDataDirSize(unsigned n)
Global getPEDllCharacteristics(void)
Global getPEFileAlignment(void)
Global getPEImageBase(void)
Global getPEisDLL()
Global getPELFANew(void)
```

36 7.1. API groups

Global getPELoaderFlags(void) Global getPEMachine() Global getPEMajorImageVersion(void) Global getPEMajorLinkerVersion(void) Global getPEMajorOperatingSystemVersion(void) Global getPEMajorSubsystemVersion(void) Global getPEMinorImageVersion(void) Global getPEMinorLinkerVersion(void) Global getPEMinorOperatingSystemVersion(void) Global getPEMinorSubsystemVersion(void) Global getPENumberOfSymbols() Global getPEPointerToSymbolTable() Global getPESectionAlignment(void) Global getPESizeOfCode(void) Global getPESizeOfHeaders(void) Global getPESizeOfHeapCommit(void) Global getPESizeOfHeapReserve(void) Global getPESizeOfImage(void) Global getPESizeOfInitializedData(void) Global getPESizeOfOptionalHeader()

```
{\bf Global~getPESizeOfStackCommit} ({\bf void})
```

Global getPESizeOfStackReserve(void)

 ${\bf Global~getPESizeOfUninitializedData(void)}$

Global getPESubsystem(void)

Global getPETimeDateStamp()

Global getPEWin32VersionValue(void)

Global getSectionRVA(unsigned i) .

 $Global\ getSectionVirtualSize(unsigned\ i)$.

Global getVirtualEntryPoint(void)

Global hasExeInfo(void)

Global hasPEInfo(void)

Global isPE64(void)

Class pe_image_data_dir

Class pe_image_file_hdr

 ${\bf Class\ pe_image_optional_hdr32}$

Class $pe_image_optional_hdr64$

Class pe_image_section_hdr

Global pe_rawaddr(uint32_t rva)

Global readPESectionName(unsigned char name[8], unsigned n)

Global readRVA(uint32_t rva, void *buf, size_t bufsize)

7.1. API groups

7.1.13. Scan control functions

Global extract_new(int32_t id)

Global bytecode_rt_error(int32_t locationid)

Global extract_set_container(uint32_t container)

```
Global foundVirus(const char *virusname)
Global input_switch(int32_t extracted_file)
Global setvirusname(const uint8_t *name, uint32_t len)
7.1.14. String operations
Global atoi(const uint8_t *str, int32_t size)
Global debug_print_str(const uint8_t *str, uint32_t len)
Global debug_print_str_nonl(const uint8_t *str, uint32_t len)
Global debug_print_str_start(const uint8_t *str, uint32_t len)
Global debug_print_uint(uint32_t a)
Global entropy_buffer(uint8_t *buffer, int32_t size)
Global hex2ui(uint32_t hex1, uint32_t hex2)
Global memchr(const void *s, int c, size t n)
Global memcmp(const void *s1, const void *s2, uint32_t n) __attribute__((__nothrow___)) _
Global memcpy(void *restrict dst, const void *restrict src, uintptr_t n) ___attribute___((___notlease.
Global memmove(void *dst, const void *src, uintptr_t n) __attribute__((__nothrow___)) ___a
Global memset(void *src, int c, uintptr_t n) __attribute__((nothrow)) __attribute__((__no
Global memstr(const uint8_t *haystack, int32_t haysize, const uint8_t *needle, int32_t needles
```

7.2. Structure types

7.2.1. cli exe info Struct Reference

Data Fields

- struct cli_exe_section * section
- uint32 t offset
- uint32_t ep
- uint16_t nsections
- uint32_t res_addr
- $uint32_t hdr_size$

7.2.1.1. Detailed Description

Executable file information

 \mathbf{PE}

7.2.1.2. Field Documentation

- 7.2.1.2.1. uint32_t ep Entrypoint of executable
- 7.2.1.2.2. uint32_t hdr_size Address size PE ONLY
- $\textbf{7.2.1.2.3. uint} \textbf{16_t nsections} \quad \text{Number of sections}$
- **7.2.1.2.4.** uint32_t offset Offset where this executable start in file (nonzero if embedded)
- 7.2.1.2.5. uint32_t res_addr Resrources RVA PE ONLY
- **7.2.1.2.6. struct cli_exe_section* section** Information about all the sections of this file. This array has **nsection** elements

7.2.2. cli_exe_section Struct Reference

- uint32_t rva
- \bullet uint32_t vsz
- uint32_t raw
- \bullet uint32_t rsz
- $uint32_t chr$
- uint32_t urva
- uint32_t uvsz
- uint32_t uraw uint32_t ursz

40 7.2. Structure types

7.2.2.1. Detailed Description

Section of executable file.

 \mathbf{PE}

7.2.2.2. Field Documentation

7.2.2.2.1. uint32_t chr Section characteristics

7.2.2.2. uint32_t raw Raw offset (in file)

7.2.2.3. uint32_t rsz Raw size (in file)

7.2.2.4. uint32_t rva Relative VirtualAddress

7.2.2.2.5. uint32_t uraw PE - unaligned PointerToRawData

7.2.2.2.6. uint32_t ursz PE - unaligned SizeOfRawData

7.2.2.7. uint32_t urva PE - unaligned VirtualAddress

 $\textbf{7.2.2.2.8. uint32_t uvsz} \quad \text{PE - unaligned VirtualSize}$

7.2.2.2.9. uint32_t vsz VirtualSize

7.2.3. cli_pe_hook_data Struct Reference

- uint32_t ep
- uint16 t nsections
- $\bullet \ \ struct \ pe_image_file_hdr \ file_hdr$
- struct pe_image_optional_hdr32 opt32
- struct pe_image_optional_hdr64 opt64
- struct pe_image_data_dir dirs [16]
- uint32_t e_lfanew
- uint32_t overlays
- int32 t overlays sz
- uint32_t hdr_size

7.2.3.1. Detailed Description

Data for the bytecode PE hook

 \mathbf{PE}

7.2.3.2. Field Documentation

7.2.3.2.1. struct pe_image_data_dir dirs[16] PE data directory header

 $7.2.3.2.2. \ uint 32_t \ e_l fanew \quad {\rm address \ of \ new \ exe \ header }$

 $\textbf{7.2.3.2.3.} \ \, \textbf{uint32_t} \ \, \textbf{ep} \quad \textbf{EntryPoint as file offset}$

7.2.3.2.4. struct pe_image_file_hdr file_hdr Header for this PE file

7.2.3.2.5. uint32_t hdr_size internally needed by rawaddr

7.2.3.2.6. uint16_t nsections Number of sections

7.2.3.2.7. struct pe_image_optional_hdr32 opt32 32-bit PE optional header

7.2.3.2.8. struct pe_image_optional_hdr64 opt64 64-bit PE optional header

7.2.3.2.9. uint32_t overlays number of overlays

7.2.3.2.10. int32_t overlays_sz size of overlays

7.2.4. DIS_arg Struct Reference

Data Fields

- enum DIS ACCESS access type
- enum DIS_SIZE access_size
- struct DIS_mem_arg mem
- enum X86REGS reg
- uint64_t other

7.2.4.1. Detailed Description

disassembled operand

Disassemble

7.2. Structure types

7.2.4.2. Field Documentation

7.2.4.2.1. enum DIS_SIZE access_size size of access

7.2.4.2.2. enum DIS_ACCESS access_type type of access

7.2.4.2.3. struct DIS_mem_arg mem memory operand

7.2.4.2.4. uint64_t other other operand

7.2.4.2.5. enum X86REGS reg register operand

7.2.5. DIS fixed Struct Reference

Data Fields

- enum X86OPS x86_opcode
- enum DIS_SIZE operation_size
- enum DIS_SIZE address_size
- uint8_t segment

7.2.5.1. Detailed Description

disassembled instruction.

Disassemble

7.2.5.2. Field Documentation

 ${\bf 7.2.5.2.1.\ enum\ DIS_SIZE\ address_size}\quad {\rm size\ of\ address}$

 ${\bf 7.2.5.2.2.\ enum\ DIS_SIZE\ operation_size}\quad {\rm size\ of\ operation}$

7.2.5.2.3. uint8_t segment segment

7.2.5.2.4. enum X86OPS x86_opcode opcode of X86 instruction

7.2.6. DIS_mem_arg Struct Reference

- enum DIS_SIZE access_size
- enum X86REGS scale_reg
- enum X86REGS add_reg
- uint8_t scale
- int32_t displacement

7.2.6.1. Detailed Description

 ${\it disassembled memory operand: scale_reg*scale} + {\it add_reg} + {\it displacement}$

Disassemble

7.2.6.2. Field Documentation

7.2.6.2.1. enum DIS_SIZE access_size size of access

7.2.6.2.2. enum X86REGS add_reg register used as displacemenet

7.2.6.2.3. int32_t displacement displacement as immediate number

7.2.6.2.4. uint8_t scale scale as immediate number

7.2.6.2.5. enum X86REGS scale_reg register used as scale

7.2.7. DISASM_RESULT Struct Reference

7.2.7.1. Detailed Description

disassembly result, 64-byte, matched by type-8 signatures

7.2.8. pe_image_data_dir Struct Reference

7.2.8.1. Detailed Description

PE data directory header

 \mathbf{PE}

7.2.9. pe_image_file_hdr Struct Reference

- uint32 t Magic
- uint16_t Machine
- \bullet uint16_t NumberOfSections
- uint32_t TimeDateStamp
- \bullet uint32_t PointerToSymbolTable
- uint32 t NumberOfSymbols
- \bullet uint16_t SizeOfOptionalHeader

7.2. Structure types

7.2.9.1. Detailed Description

Header for this PE file

 \mathbf{PE}

7.2.9.2. Field Documentation

7.2.9.2.1. uint16_t Machine CPU this executable runs on, see libclamav/pe.c for possible values

7.2.9.2.2. uint32_t Magic PE magic header: $PE \setminus 0 \setminus 0$

7.2.9.2.3. uint16_t NumberOfSections Number of sections in this executable

7.2.9.2.4. uint32_t NumberOfSymbols debug

7.2.9.2.5. uint32_t PointerToSymbolTable debug

 $7.2.9.2.6. uint16_t SizeOfOptionalHeader == 224$

7.2.9.2.7. uint32_t TimeDateStamp Unreliable

7.2.10. pe_image_optional_hdr32 Struct Reference

- uint8 t MajorLinkerVersion
- $\bullet \quad uint8_t \ MinorLinkerVersion$
- uint32_t SizeOfCode
- uint32_t SizeOfInitializedData
- uint32_t SizeOfUninitializedData
- $\bullet \ \ uint 32_t \ Image Base$
- uint32_t SectionAlignment
- uint32_t FileAlignment
- uint16 t MajorOperatingSystemVersion
- uint16_t MinorOperatingSystemVersion
- uint16 t MajorImageVersion
- uint16_t MinorImageVersion
- uint32_t CheckSum
- uint32_t NumberOfRvaAndSizes

7.2.10.1. Detailed Description

32-bit PE optional header

 \mathbf{PE}

7.2.10.2. Field Documentation

7.2.10.2.1. uint32_t CheckSum NT drivers only

7.2.10.2.2. uint32_t FileAlignment usually 32 or 512

 $\textbf{7.2.10.2.3. uint32_t ImageBase} \quad \text{multiple of 64 KB}$

7.2.10.2.4. uint16_t MajorImageVersion unreliable

7.2.10.2.5. uint8_t MajorLinkerVersion unreliable

7.2.10.2.6. uint16_t MajorOperatingSystemVersion not used

7.2.10.2.7. uint16_t MinorImageVersion unreliable

 $7.2.10.2.8. \ uint8_t \ MinorLinkerVersion \ \ unreliable$

7.2.10.2.9. uint16_t MinorOperatingSystemVersion not used

 $7.2.10.2.10.\ uint 32_t\ Number Of Rva And Sizes \quad unreliable$

7.2.10.2.11. uint32_t SectionAlignment usually 32 or 4096

 $7.2.10.2.12. \ uint 32_t \ Size Of Code \quad {\rm unreliable}$

 $7.2.10.2.13.\ uint 32_t\ Size Of Initialized Data\quad unreliable$

 $7.2.10.2.14.\ uint 32_t\ Size Of Uninitialized Data\quad unreliable$

7.2.11. pe_image_optional_hdr64 Struct Reference

- uint8_t MajorLinkerVersion
- uint8 t MinorLinkerVersion
- uint32 t SizeOfCode
- \bullet uint32_t SizeOfInitializedData
- uint32_t SizeOfUninitializedData
- uint64_t ImageBase
- uint32_t SectionAlignment

7.2. Structure types

- uint32_t FileAlignment
- uint16_t MajorOperatingSystemVersion
- uint16_t MinorOperatingSystemVersion
- uint16_t MajorImageVersion
- uint16_t MinorImageVersion
- uint32_t CheckSum
- uint32 t NumberOfRvaAndSizes

7.2.11.1. Detailed Description

PE 64-bit optional header

 \mathbf{PE}

- 7.2.11.2. Field Documentation
- 7.2.11.2.1. uint32_t CheckSum NT drivers only
- **7.2.11.2.2. uint32_t FileAlignment** usually 32 or 512
- 7.2.11.2.3. uint64_t ImageBase multiple of 64 KB
- 7.2.11.2.4. uint16_t MajorImageVersion unreliable
- $7.2.11.2.5.\ uint8_t\ MajorLinkerVersion\quad unreliable$
- 7.2.11.2.6. uint16_t MajorOperatingSystemVersion not used
- 7.2.11.2.7. uint16_t MinorImageVersion unreliable
- 7.2.11.2.8. uint8_t MinorLinkerVersion unreliable
- 7.2.11.2.9. uint16_t MinorOperatingSystemVersion not used
- $7.2.11.2.10.\ uint 32_t\ Number Of Rva And Sizes \quad unreliable$
- **7.2.11.2.11. uint32_t SectionAlignment** usually 32 or 4096
- $7.2.11.2.12. \ uint 32_t \ Size Of Code \quad {\rm unreliable}$

 ${\bf 7.2.11.2.13.\ uint 32_t\ Size Of Initialized Data}\quad {\bf unreliable}$

7.2.11.2.14. uint32_t SizeOfUninitializedData unreliable

7.2.12. pe_image_section_hdr Struct Reference

Data Fields

- uint8_t Name [8]
- uint32_t SizeOfRawData
- uint32_t PointerToRawData
- uint32 t PointerToRelocations
- uint32 t PointerToLinenumbers
- uint16 t NumberOfRelocations
- uint16_t NumberOfLinenumbers

7.2.12.1. Detailed Description

PE section header

 \mathbf{PE}

7.2.12.2. Field Documentation

 $7.2.12.2.1.\ uint8_t\ Name[8]\quad \mathrm{may\ not\ end\ with\ NULL}$

7.2.12.2.2. uint16_t NumberOfLinenumbers object files only

7.2.12.2.3. uint16_t NumberOfRelocations object files only

7.2.12.2.4. uint32_t PointerToLinenumbers object files only

7.2.12.2.5. uint32_t PointerToRawData offset to the section's data

7.2.12.2.6. uint32_t PointerToRelocations object files only

7.2.12.2.7. uint32_t SizeOfRawData multiple of FileAlignment

7.3. Low level API

7.3.1. bytecode_api.h File Reference

Enumerations

- enum Bytecode Kind { BC_GENERIC = 0 , BC_LOGICAL = 256, BC_PE_UNPACKER } 7.3. Low level API

- enum { PE_INVALID_RVA = 0xFFFFFFFF }
- enum FunctionalityLevels
- enum pdf_phase
- enum pdf_flag
- enum pdf_objflags
- enum { SEEK_SET = 0, SEEK_CUR, SEEK_END }

Functions

- uint32_t test1 (uint32_t a, uint32_t b)
- $int32_t$ read $(uint8_t *data, int32_t$ size)

Reads specified amount of bytes from the current file into a buffer. Also moves current position in the file.

• int32_t write (uint8_t *data, int32_t size)

Writes the specified amount of bytes from a buffer to the current temporary file.

• int32_t seek (int32_t pos, uint32_t whence)

Changes the current file position to the specified one.

- uint32_t setvirusname (const uint8_t *name, uint32_t len)
- uint32_t debug_print_str (const uint8_t *str, uint32_t len)
- uint32 t debug print uint (uint32 t a)
- uint32 t disasm x86 (struct DISASM RESULT *result, uint32 t len)
- uint32 t pe rawaddr (uint32 t rva)
- int32_t file_find (const uint8_t *data, uint32_t len)
- int32_t file_byteat (uint32_t offset)
- void * malloc (uint32 t size)
- uint32 t test2 (uint32 t a)
- int32_t get_pe_section (struct cli_exe_section *section, uint32_t num)
- int32_t fill_buffer (uint8_t *buffer, uint32_t len, uint32_t filled, uint32_t cursor, uint32_t fill)
- int32_t extract_new (int32_t id)
- int32_t read_number (uint32_t radix)
- int32_t hashset_new (void)
- int32_t hashset_add (int32_t hs, uint32_t key)
- int32_t hashset_remove (int32_t hs, uint32_t key)
- int32_t hashset_contains (int32_t hs, uint32_t key)
- int32 t hashset done (int32 t id)
- int32_t hashset_empty (int32_t id)
- int32_t buffer_pipe_new (uint32_t size)
- int32 t buffer pipe new fromfile (uint32 t pos)
- uint32_t buffer_pipe_read_avail (int32_t id)
- uint8_t * buffer_pipe_read_get (int32_t id, uint32_t amount)
- int32 t buffer pipe read stopped (int32 t id, uint32 t amount)
- uint32_t buffer_pipe_write_avail (int32_t id)
- uint8_t * buffer_pipe_write_get (int32_t id, uint32_t size)
- int32_t buffer_pipe_write_stopped (int32_t id, uint32_t amount)
- int32_t buffer_pipe_done (int32_t id)

```
• int32_t inflate_init (int32_t from_buffer, int32_t to_buffer, int32_t windowBits)
• int32 t inflate process (int32 t id)
• int32 t inflate done (int32 t id)
• int32 t bytecode rt error (int32 t locationid)
• int32 t jsnorm init (int32 t from buffer)
• int32_t jsnorm_process (int32_t id)
• int32_t jsnorm_done (int32_t id)
• int32 t ilog2 (uint32 t a, uint32 t b)
• int32 t ipow (int32 t a, int32 t b, int32 t c)
• uint32_t iexp (int32_t a, int32_t b, int32_t c)
• int32_t isin (int32_t a, int32_t b, int32_t c)
• int32_t icos (int32_t a, int32_t b, int32_t c)
 int32 t memstr (const uint8 t *haystack, int32 t haysize, const uint8 t *needle, int32 t
  needlesize)
• int32 t hex2ui (uint32 t hex1, uint32 t hex2)
• int32_t atoi (const uint8_t *str, int32_t size)
• uint32_t debug_print_str_start (const uint8_t *str, uint32_t len)
• uint32_t debug_print_str_nonl (const uint8_t *str, uint32_t len)
• uint32 t entropy buffer (uint8 t *buffer, int32 t size)
• int32 t map new (int32 t keysize, int32 t valuesize)
• int32_t map_addkey (const uint8_t *key, int32_t ksize, int32_t id)
• int32 t map setvalue (const uint8 t *value, int32 t vsize, int32 t id)
• int32_t map_remove (const uint8_t *key, int32_t ksize, int32_t id)
• int32_t map_find (const uint8_t *key, int32_t ksize, int32_t id)
• int32 t map getvaluesize (int32 t id)
• uint8_t * map_getvalue (int32_t id, int32_t size)
• int32 t map done (int32 t id)
• int32_t file_find_limit (const uint8_t *data, uint32_t len, int32_t maxpos)
• uint32_t engine_functionality_level (void)
• uint32 t engine dconf level (void)
• uint32 t engine scan options (void)
• uint32 t engine db options (void)
• int32_t extract_set_container (uint32_t container)
• int32_t input_switch (int32_t extracted_file)
• uint32 t get environment (struct cli environment *env, uint32 t len)
• uint32 t disable bytecode if (const int8 t *reason, uint32 t len, uint32 t cond)
• uint32 t disable jit if (const int8 t *reason, uint32 t len, uint32 t cond)
• int32_t version_compare (const uint8_t *lhs, uint32_t lhs_len, const uint8_t *rhs, uint32_-
  t rhs len)
• uint32_t check_platform (uint32_t a, uint32_t b, uint32_t c)
• int32 t pdf get obj num (void)
```

• int32 t pdf get flags (void)

int32_t pdf_set_flags (int32_t flags)
int32_t pdf_lookupobj (uint32_t id)
uint32_t pdf_getobjsize (int32_t objidx)

• uint8_t * pdf_getobj (int32_t objidx, uint32_t amount)

50 7.3. Low level API

- int32_t pdf_get_phase (void)
- int32_t pdf_get_dumpedobjid (void)
- int32_t matchicon (const uint8_t *group1, int32_t group1_len, const uint8_t *group2, int32_t group2_len)

Variables

- const uint32_t __clambc_match_counts [64] Logical signature match counts.
- $\bullet \ \ const \ uint 32_t \ __clambc_match_offsets \ [64]$

Logical signature match offsets This is a low-level variable, use the Macros in bytecode_local.h instead to access it.

- const uint32_t ___clambc_filesize [1]
- const uint16_t __clambc_kind

7.3.1.1. Detailed Description

7.3.1.2. Enumeration Type Documentation

7.3.1.2.1. anonymous enum

Enumerator:

```
PE_INVALID_RVA Invalid RVA specified
```

7.3.1.2.2. anonymous enum

Enumerator:

```
SEEK_SET set file position to specified absolute position
SEEK_CUR set file position relative to current position
SEEK_END set file position relative to file end
```

7.3.1.2.3. enum BytecodeKind Bytecode trigger kind

Enumerator:

```
BC\_GENERIC generic bytecode, not tied a specific hook BC\_LOGICAL triggered by a logical signature BC\_PE\_UNPACKER a PE unpacker
```

7.3.1.2.4. enum FunctionalityLevels LibClamAV functionality level constants

7.3.1.2.5. enum pdf_flag PDF flags

7.3.1.2.6. enum pdf_objflags PDF obj flags

7.3.1.2.7. enum pdf_phase Phase of PDF parsing

7.3.1.3. Function Documentation

7.3.1.3.1. int32_t atoi (const uint8_t * str, int32_t size) Converts string to positive number.

Parameters

str	buffer
size	size of str

Returns

>0 string converted to number if possible, -1 on error

String operation

7.3.1.3.2. int32_t buffer_pipe_done (int32_t id) Deallocate memory used by buffer.

Data structure

After this all attempts to use this buffer will result in error. All buffer_pipes are automatically deallocated when bytecode finishes execution.

Parameters

id ID of buffer pipe

Returns

0 on success

 $7.3.1.3.3.\ int 32_t\ buffer_pipe_new$ ($\ uint 32_t\ size$) Creates a new pipe with the specified buffer size

Data structure

Parameters

```
size size of buffer
```

Returns

ID of newly created buffer_pipe

7.3.1.3.4. int32_t buffer_pipe_new_fromfile (uint32_t pos) Same as buffer_pipe_new, except the pipe's input is tied

Data structure

52 7.3. Low level API

File operation

to the current file, at the specified position.

Parameters

pos	starting position of pipe input in current file

Returns

ID of newly created buffer_pipe

7.3.1.3.5. uint32_t buffer_pipe_read_avail (int32_t id) Returns the amount of bytes available to read.

Data structure

Parameters

```
id \mid \mathrm{ID} \; \mathrm{of} \; \mathrm{buffer\_pipe}
```

Returns

amount of bytes available to read

7.3.1.3.6. uint8_t* buffer_pipe_read_get (int32_t id, uint32_t amount) Returns a pointer to the buffer for reading.

Data structure

The 'amount' parameter should be obtained by a call to buffer_pipe_read_avail().

Parameters

id	ID of buffer_pipe
amount	to read

Returns

pointer to buffer, or NULL if buffer has less than specified amount

7.3.1.3.7. int32_t buffer_pipe_read_stopped (int32_t id, uint32_t amount)

Data structure

Updates read cursor in buffer_pipe.

Parameters

id	ID of buffer_pipe
amount	amount of bytes to move read cursor

Returns

0 on success

7.3.1.3.8. uint32_t buffer_pipe_write_avail (int32_t id) Returns the amount of bytes available for writing.

Data structure

Parameters

```
id ID of buffer_pipe
```

Returns

amount of bytes available for writing

Data structure

Returns pointer to writable buffer. The 'amount' parameter should be obtained by a call to buffer_pipe_write_avail().

Parameters

id ID of buffer_pipe	
size	amount of bytes to write

Returns

pointer to write buffer, or NULL if requested amount is more than what is available in the buffer

7.3.1.3.10. int32_t buffer_pipe_write_stopped (int32_t id, uint32_t amount) Updates the write cursor in buffer_pipe.

Data structure

Parameters

```
id ID of buffer_pipe
amount amount of bytes to move write cursor
```

Returns

0 on success

 $7.3.1.3.11. \ int 32_t \ by tecode_rt_error \ (\ int 32_t \ location id \) \ \ Report \ a \ runtime \ error \ at the specified location ID.$

Scan

Parameters

```
locationid \mid (line << 8) \mid (column \& 0xff)
```

54 7.3. Low level API

Returns

0

7.3.1.3.12. uint32_t check_platform (uint32_t a, uint32_t b, uint32_t c) Disables the JIT if the platform id matches. 0xff can be used instead of a field to mark ANY.

Parameters

a	- os_category $<<$ 24 arch $<<$ 20 compiler $<<$ 16 flevel $<<$ 8 dconf
b	- big_endian << 28 sizeof_ptr << 24 cpp_version
c	- os_features << 24 c_version

Returns

0 - no match 1 - match

Environment

7.3.1.3.13. uint32_t debug_print_str (const uint8_t * str, uint32_t len) Prints a debug message.

Parameters

in	str	Message to print
in	len	length of message to print

Returns

0

String operation

7.3.1.3.14. uint32_t debug_print_str_nonl (const uint8_t * str, uint32_t len) Prints a debug message with a trailing newline, and not preceded by 'LibClamAV debug'.

Parameters

str	the string
len	length of str

Returns

0

String operation

7.3.1.3.15. uint32_t debug_print_str_start (const uint8_t * str, uint32_t len) Prints a debug message with a trailing newline, but preceded by 'LibClamAV debug'.

Parameters

str	the string

len length of str

Returns

0

String operation

7.3.1.3.16. uint32_t debug_print_uint (uint32_t a) Prints a number as a debug message. This is like debug_print_str_nonl!

Parameters

in	a	number to print

Returns

0

String operation

7.3.1.3.17. uint32_t disable_bytecode_if (const int8_t * reason, uint32_t len, uint32_t cond) Disables the bytecode completely if condition is true. Can only be called from the BC_STARTUP bytecode.

Parameters

reason - why the bytecode had to be disabled	
len - length of reason	
cond	- condition

Returns

0 - auto mode 1 - JIT disabled 2 - fully disabled

Environment

7.3.1.3.18. uint32_t disable_jit_if (const int8_t * reason, uint32_t len, uint32_t cond) Disables the JIT completely if condition is true. Can only be called from the BC_STARTUP bytecode.

Parameters

reason	- why the JIT had to be disabled
len	- length of reason
cond	- condition

Returns

0 - auto mode 1 - JIT disabled 2 - fully disabled

7.3. Low level API

Environment

7.3.1.3.19. uint32_t disasm_x86 (struct DISASM_RESULT * result, uint32_t len) Disassembles starting from current file position, the specified amount of bytes.

Parameters

out	result	pointer to struct holding result
in	len	how many bytes to disassemble

Returns

0 for success

You can use lseek to disassemble starting from a different location. This is a low-level API, the result is in ClamAV type-8 signature format (64 bytes/instruction).

See also

DisassembleAt

Disassemble

 $7.3.1.3.20.\ uint32_t\ engine_db_options$ (void) Returns the current engine's db options.

Returns

 $CL_DB_* flags$

Engine query

Returns

an integer representing the DCONF (security fixes) level.

Engine query

7.3.1.3.22. uint32_t engine_functionality_level (void) Returns the current engine (feature) functionality level. To map these to ClamAV releases, compare it with FunctionalityLevels.

Returns

an integer representing current engine functionality level.

Engine query

Returns

CL_SCAN* flags

Engine query

7.3.1.3.24. uint32_t entropy_buffer (uint8_t * buffer, int32_t size) Returns an approximation for the entropy of buffer.

Parameters

$\it buffer$	input buffer
size	size of buffer

Returns

entropy estimation $*2^{26}$

String operation

7.3.1.3.25. int32_t extract_new (int32_t id) Prepares for extracting a new file, if we've already extracted one it scans it.

Scan

Parameters

in	id	an id for the new file (for example position in container)
----	----	--

Returns

1 if previous extracted file was infected

 $7.3.1.3.26.\ int 32_t\ extract_set_container\ (\ uint 32_t\ container\)\ \ Sets\ the\ container\ type\ for\ the\ currently\ extracted\ file.$

Parameters

```
container | container type (CL_TYPE_*)
```

Returns

current setting for container (CL_TYPE_ANY default)

Scan

58 7.3. Low level API

7.3.1.3.27. int32_t file_byteat (uint32_t offset) Read a single byte from current file

File operation

Parameters

offset	file offset

Returns

byte at offset off in the current file, or -1 if offset is invalid

7.3.1.3.28. int32_t file_find (const uint8_t * data, uint32_t len) Looks for the specified sequence of bytes in the current file.

File operation

Parameters

in	data	the sequence of bytes to look for
	len	length of data, cannot be more than 1024

Returns

offset in the current file if match is found, -1 otherwise

7.3.1.3.29. int32_t file_find_limit (const uint8_t * data, uint32_t len, int32_t maxpos) Looks for the specified sequence of bytes in the current file, up to the specified position.

Parameters

in	data	the sequence of bytes to look for
	len	length of data, cannot be more than 1024
	maxpos	maximum position to look for a match, note that this is 1 byte after the
		end of last possible match: $match_pos + len < maxpos$

Returns

offset in the current file if match is found, -1 otherwise

File operation

7.3.1.3.30. int32_t fill_buffer (uint8_t * buffer, uint32_t len, uint32_t filled, uint32_t cursor, uint32_t fill) Fills the specified buffer with at least fill bytes.

File operation

Parameters

out	buffer	the buffer to fill
in	len	length of buffer
in	filled	how much of the buffer is currently filled
in	cursor	position of cursor in buffer
in	fill	amount of bytes to fill in (0 is valid)

Returns

<0 on error, 0 on EOF, number bytes available in buffer (starting from 0) The character at the cursor will be at position 0 after this call.

7.3.1.3.31. uint32_t get_environment (struct cli_environment * env, uint32_t len) Queries the environment this bytecode runs in. Used by BC_STARTUP to disable bytecode when bugs are known for the current platform.

Parameters

out	env	- the full environment
	len	- size of env

Returns

0

Environment

7.3.1.3.32. int32_t get_pe_section (struct cli_exe_section * section, uint32_t num) Gets information about the specified PE section.

 \mathbf{PE}

Parameters

out	section	PE section information will be stored here
in	num	PE section number

Returns

0 - success -1 - failure

7.3.1.3.33. int32_t hashset_add (int32_t hs, uint32_t key) Add a new 32-bit key to the hashset.

Data structure

Parameters

hs	ID of hashset (from hashset_new)
key	the key to add

7.3. Low level API

Returns

0 on success

7.3.1.3.34. int32_t hashset_contains (int32_t hs, uint32_t key) Returns whether the hashset contains the specified key.

Data structure

Parameters

hs	ID of hashset (from hashset_new)
key	the key to lookup

Returns

1 if found, 0 if not found, <0 on invalid hashset ID

7.3.1.3.35. int32_t hashset_done (int32_t id) Deallocates the memory used by the specified hashset.

Data structure

Trying to use the hashset after this will result in an error. The hashset may not be used after this. All hashsets are automatically deallocated when bytecode finishes execution.

Parameters

id	I ID of hashset (from hashset_new)
----	------------------------------------

Returns

0 on success

7.3.1.3.36. int32_t hashset_empty (int32_t id) Returns whether the hashset is empty.

Data structure

Parameters

id of has	shset (from hashset_new)	

Returns

0 on success

7.3.1.3.37. int32_t hashset_new (void) Creates a new hashset and returns its id.

Data structure

Returns

ID for new hashset

7.3.1.3.38. int32_t hashset_remove (int32_t hs, uint32_t key) Remove a 32-bit key from the hashset.

Data structure

Parameters

hs	ID of hashset (from hashset_new)
key	the key to add

Returns

0 on success

7.3.1.3.39. int32_t hex2ui (uint32_t hex1, uint32_t hex2) Returns hexadecimal characters hex1 and hex2 converted to 8-bit number.

Parameters

hex1	hexadecimal character
hex2	hexadecimal character

Returns

hex1 hex2 converted to 8-bit integer, -1 on error

String operation

7.3.1.3.40. int32_t icos (int32_t a, int32_t b, int32_t c) Returns c* $\cos(a/b)$.

Parameters

a	integer
b	integer
c	integer

Returns

c*sin(a/b)

Math function

7.3.1.3.41. uint32_t iexp (int32_t a, int32_t b, int32_t c) Returns exp(a/b)*c

Parameters

a	integer
b	integer
c	integer

7.3. Low level API

Returns

c*exp(a/b)

Math function

7.3.1.3.42. int32_t ilog2 (uint32_t a, uint32_t b) Returns $2^{26*\log 2(a/b)}$

Parameters

a	input
b	input

Returns

 $2^{2} = 100$

Math function

7.3.1.3.43. int32_t inflate_done (int32_t id) Deallocates inflate data structure. Using the inflate data structure after this will result in an error. All inflate data structures are automatically deallocated when bytecode finishes execution.

Data structure

Parameters

$id \mid ext{ID of inflate data structure}$
--

Returns

0 on success.

7.3.1.3.44. int32_t inflate_init (int32_t $from_buffer$, int32_t to_buffer , int32_t windowBits) Initializes inflate data structures for decompressing data

Data structure

'from buffer' and writing uncompressed uncompressed data 'to buffer'.

Parameters

$from_buff$	er ID of buffer_pipe to read compressed data from
to_buff	er ID of buffer_pipe to write decompressed data to
windowBi	ts (see zlib documentation)

Returns

ID of newly created inflate data structure, <0 on failure

7.3.1.3.45. int32_t inflate_process (int32_t id) Inflate all available data in the input buffer, and write to output buffer. Stops when the input buffer becomes empty, or write buffer becomes full. Also attempts to recover from corrupted inflate stream (via inflateSync). This function can be called repeatedly on success after filling the input buffer, and flushing the output buffer. The inflate stream is done processing when 0 bytes are available from output buffer, and input buffer is not empty.

Data structure

Parameters

id	ID of inflate data structure
----	------------------------------

Returns

0 on success, zlib error code otherwise

7.3.1.3.46. int32_t input_switch (int32_t extracted_file) Toggles the read/seek API to read from the currently extracted file, and back. You must call seek after switching inputs to position the cursor to a valid position.

Parameters

```
extracted_file | 1 - switch to reading from extracted file, 0 - switch back to original input
```

Returns

-1 on error (if no extracted file exists) 0 on success

Scan

7.3.1.3.47. int32_t ipow (int32_t a, int32_t b, int32_t c) Returns c*a^b.

Parameters

a	integer
b	integer
c	integer

Returns

c*pow(a,b)

Math function

7.3.1.3.48. int32_t isin (int32_t a, int32_t b, int32_t c) Returns c*sin(a/b).

Parameters

a	integer
b	integer
c	integer

7.3. Low level API

Returns

c*sin(a/b)

Math function

7.3.1.3.49. int32_t jsnorm_done (int32_t id) Flushes JS normalizer.

JavaScript

Parameters

id ID of js normalizer to flush

Returns

0 - success -1 - failure

7.3.1.3.50. int32_t jsnorm_init (int32_t from_buffer) Initializes JS normalizer for reading 'from_buffer'. Normalized JS will be written to a single tempfile, one normalized JS per line, and automatically scanned when the bytecode finishes execution.

JavaScript

Parameters

from_buffer ID of	ouffer_pipe to read javascript from	

Returns

ID of JS normalizer, <0 on failure

7.3.1.3.51. int32_t jsnorm_process (int32_t id) Normalize all javascript from the input buffer, and write to tempfile. You can call this function repeatedly on success, if you (re)fill the input buffer.

JavaScript

Parameters

id ID of JS normalizer

Returns

0 on success, <0 on failure

7.3.1.3.52. void* malloc (uint32_t size) Allocates memory. Currently this memory is freed automatically on exit from the bytecode, and there is no way to free it sooner.

Data structure

Parameters

size amount of memory to allocate in bytes

Returns

pointer to allocated memory

7.3.1.3.53. int32_t map_addkey (const uint8_t * key, int32_t ksize, int32_t id) Inserts the specified key/value pair into the map.

Parameters

id	id of table
key	key
ksize	size of key

Returns

0 - if key existed before 1 - if key didn't exist before $<\!0$ - if ksize doesn't match keysize specified at table creation

Data structure

7.3.1.3.54. int32_t map_done (int32_t id) Deallocates the memory used by the specified map. Trying to use the map after this will result in an error. All maps are automatically deallocated when the bytecode finishes execution.

Parameters

id id of map

Returns

0 - success -1 - invalid map

Data structure

7.3.1.3.55. int32_t map_find (const uint8_t * key, int32_t ksize, int32_t id) Looks up key in map. The map remember the last looked up key (so you can retrieve the value).

Parameters

id	id of map
key	key
ksize	size of key

Returns

0 - if not found 1 - if found $<\!0$ - if ksize doesn't match the size specified at table creation

Data structure

7.3. Low level API

 $7.3.1.3.56. \ uint8_t* \ map_getvalue \ (\ int32_t \ \emph{id}, \ int32_t \ \emph{size} \) \ \ \text{Returns the value obtained during last map_find}.$

Parameters

id	id of map.
size	size of value (obtained from map_getvaluesize)

Returns

value

Data structure

 $7.3.1.3.57. \ \, int 32_t \ \, map_get value size \left(\ \, int 32_t \ \, id \ \, \right) \ \, \text{Returns the size of value obtained during last map_find.}$

Parameters

id	id of man
100	id of map.

Returns

size of value

Data structure

 $7.3.1.3.58.\ int 32_t\ map_new\ (\ int 32_t\ keysize,\ int 32_t\ value size\)\ \ {\it Creates\ a\ new\ map\ and\ returns\ its\ id.}$

Parameters

keysize	size of key	
value size	size of value, if 0 then value is allocated separately	

Returns

ID of new map

Data structure

7.3.1.3.59. int32_t map_remove (const uint8_t * key, int32_t ksize, int32_t id) Remove an element from the map.

Parameters

id	id of map
key	key
ksize	size of key

Returns

0 on success, key was present 1 if key was not present <0 if ksize doesn't match keysize

specified at table creation

Data structure

7.3.1.3.60. int32_t map_set value (const uint8_t * value, int32_t vsize, int32_t id) Sets the value for the last inserted key with map_add key.

Parameters

$id \mid \mathrm{id} \; \mathrm{of} \; \mathrm{table}$		id of table
	value	value
	vsize	size of value

Returns

0 - if update was successful <0 - if there is no last key

Data structure

7.3.1.3.61. int32_t matchicon (const uint8_t * group1, int32_t group1_len, const uint8_t * group2, int32_t group2_len) Attempts to match current executable's icon against the specified icon groups.

Icon

Parameters

in	group1	- same as GROUP1 in LDB signatures
	$group1_len$	- length of group1
in	group2	- same as GROUP2 in LDB signatures
	$group2_len$	- length of group2

Returns

-1 - invalid call, or sizes (only valid for PE hooks) 0 - not a match 1 - match

 $7.3.1.3.62.\ int 32_t\ memstr\ (\ const\ uint 8_t\ *\ haystack,\ int 32_t\ haysize,\ const\ uint 8_t\ *\ needle,\ int 32_t\ needle size\)\ Return\ position\ of\ match,\ -1\ otherwise.$

Parameters

haystack	buffer to search	
hay size	e size of haystack	
needle substring to search		
needlesize size of needle		

Returns

location of match, -1 otherwise

String operation

 $7.3.1.3.63. \ int 32_t \ pdf_get_dumped objid \ (\ \ void \ \) \ \ \mathrm{Return} \ the \ \mathrm{currently} \ \mathrm{dumped} \ \mathrm{obj} \ \mathrm{index}.$

PDF

Valid only in PDF_PHASE_POSTDUMP.

Returns

>=0 - object index -1 - invalid phase

 $7.3.1.3.64.\ int32_t\ pdf_get_flags$ (void) Return the flags for the entire PDF (as set so far).

Returns

-1 - if not called from PDF hook >=0 - pdf flags

PDF

7.3.1.3.65. int32_t pdf_get_obj_num (void) Return number of pdf objects

Returns

-1 - if not called from PDF hook >=0 - number of PDF objects

PDF

7.3.1.3.66. int32_t pdf_get_phase (void) Return an 'enum pdf_phase'.

PDF

Identifies at which phase this bytecode was called.

Returns

the current pdf_phase

7.3.1.3.67. uint8_t* pdf_getobj (int32_t objidx, uint32_t amount) Return the undecoded object.

PDF

Meant only for reading, write modifies the fmap buffer, so avoid!

Parameters

	- object index (from 0), not object id!
amount	- size returned by pdf_getobjsize (or smaller)

Returns

NULL - invalid objidx/amount pointer - pointer to original object

7.3.1.3.68. uint32_t pdf_getobjsize (int32_t objidx) Return the size of the specified PDF obj.

PDF

Parameters

objidx - object index (from 0), not object id!

Returns

0 - if not called from PDF hook, or invalid objnum >=0 - size of object

7.3.1.3.69. int32_t pdf_lookupobj (uint32_t id) Lookup pdf object with specified id.

PDF

Parameters

id - pdf id (objnumber << 8 | generationid)

Returns

-1 - if object id doesn't exist >=0 - object index

7.3.1.3.70. int32_t pdf_set_flags (int32_t flags) Sets the flags for the entire PDF. It is recommended that you retrieve old flags, and just add new ones.

PDF

Parameters

flags - flags to set.

Returns

0 - success -1 - invalid phase

7.3.1.3.71. uint32_t pe_rawaddr (uint32_t rva) Converts a RVA (Relative Virtual Address) to an absolute PE file offset.

Parameters

rva a rva address from the PE file

Returns

absolute file offset mapped to the rva, or PE_INVALID_RVA if the rva is invalid.

 \mathbf{PE}

7.3.1.3.72. int32_t read (uint8_t * data, int32_t size) Reads specified amount of bytes from the current file into a buffer. Also moves current position in the file.

Parameters

in	size	amount of bytes to read
out	data	pointer to buffer where data is read into

Returns

amount read.

File operation

7.3.1.3.73. int 32_t read_number (uint 32_t radix) Reads a number in the specified radix starting from the current position.

File operation

Non-numeric characters are ignored.

Parameters

in

Returns

the number read

 $7.3.1.3.74.\ int 32_t\ seek$ ($int 32_t\ pos,\ uint 32_t\ whence$) Changes the current file position to the specified one.

See also

```
SEEK_SET, SEEK_CUR, SEEK_END
```

Parameters

in	pos	offset (absolute or relative depending on whence param)
in	whence	one of SEEK_SET, SEEK_CUR, SEEK_END

Returns

absolute position in file

File operation

7.3.1.3.75. uint32_t setvirus name (const uint8_t * name, uint32_t len) Sets the name of the virus found.

Parameters

in	name	the name of the virus
in	len	length of the virusname

Returns

0

Scan

7.3.1.3.76. uint32_t test1 (uint32_t a, uint32_t b) Test api.

Parameters

a	0xf00dbeef
b	0xbeeff00d

Returns

0x12345678 if parameters match, 0x55 otherwise

7.3.1.3.77. uint32_t test2 (uint32_t
$$a$$
) Test api2.

Parameters

a	0xf00d

Returns

0xd00f if parameter matches, 0x5555 otherwise

7.3.1.3.78. int32_t version_compare (const uint8_t * lhs, uint32_t lhs_len, const uint8_t * rhs, uint32_t rhs_len) Compares two version numbers.

Parameters

in	lhs	- left hand side of comparison
	lhs_len	- length of lhs
in	rhs	- right hand side of comparison
	rhs_len	- length of rhs

Returns

Environment

7.3.1.3.79. int32_t write (uint8_t * data, int32_t size) Writes the specified amount of bytes from a buffer to the current temporary file.

Parameters

in	data	pointer to buffer of data to write

in	size	amount of bytes to write size bytes to temporary file, from the buffer
		pointed to byte

Returns

amount of bytes successfully written

File operation

7.3.1.4. Variable Documentation

7.3.1.4.1. const uint32_t ___clambc_filesize[1] File size (max 4G).

Global variable

7.3.1.4.2. const uint16_t ___clambc_kind Kind of the bytecode

Global variable

 $7.3.1.4.3. \ const \ uint 32_t \ __clambc_match_counts [64] \ \ Logical \ signature \ match \ counts.$ This is a low-level variable, use the Macros in bytecode_local.h instead to access it.

Global variable

 $7.3.1.4.4.\ const\ uint 32_t\ __clambc_match_offsets [64]\ \ Logical\ signature\ match\ offsets$ This is a low-level variable, use the Macros in bytecode_local.h instead to access it.

Global variable

 $\textbf{7.3.1.4.5. struct cli_pe_hook_data} \ __clambc_pedata \ \ PE \ \mathrm{data}, \ \mathrm{if \ this \ is \ a} \ PE \ \mathrm{hook}.$

Global variable

7.3.2. bytecode_disasm.h File Reference

Data Structures

• struct DISASM_RESULT

Enumerations

```
• enum X86OPS {,
 OP AAA, OP AAD, OP AAM, OP AAS,
 OP_ADD, OP_ADC, OP_AND, OP_ARPL,
 OP BOUND, OP BSF, OP BSR, OP BSWAP,
 OP_BT, OP_BTC, OP_BTR, OP_BTS,
 OP_CALL, OP_CDQ, OP_CWDE, OP_CBW,
 OP_CLC, OP_CLD, OP_CLI, OP_CLTS,
 OP_CMC, OP_CMOVO, OP_CMOVNO, OP_CMOVC,
 OP CMOVNC, OP CMOVZ, OP CMOVNZ, OP CMOVBE,
 OP_CMOVA, OP_CMOVS, OP_CMOVNS, OP_CMOVP,
 OP_CMOVNP, OP_CMOVL, OP_CMOVGE, OP_CMOVLE,
 OP_CMOVG, OP_CMP, OP_CMPSD, OP_CMPSW,
 OP CMPSB, OP CMPXCHG, OP CMPXCHG8B, OP CPUID,
 OP_DAA, OP_DAS, OP_DEC, OP_DIV,
 OP ENTER, OP FWAIT, OP HLT, OP IDIV,
 OP_IMUL, OP_INC, OP_IN, OP_INSD,
 OP INSW, OP INSB, OP INT, OP INT3,
 OP_INTO, OP_INVD, OP_INVLPG, OP_IRET,
 OP_JO, OP_JNO, OP_JC, OP_JNC,
 OP_JZ, OP_JNZ, OP_JBE, OP_JA,
 OP_JS, OP_JNS, OP_JP, OP_JNP,
 OP JL, OP JGE, OP JLE, OP JG,
 OP_JMP, OP_LAHF, OP_LAR, OP_LDS,
 OP_LES, OP_LFS, OP_LGS, OP_LEA,
 OP_LEAVE, OP_LGDT, OP_LIDT, OP_LLDT,
 OP_PREFIX_LOCK, OP_LODSD, OP_LODSW, OP_LODSB,
 OP_LOOP, OP_LOOPE, OP_LOOPNE, OP_JECXZ,
 OP LSL, OP LSS, OP LTR, OP MOV,
 OP_MOVSD, OP_MOVSW, OP_MOVSB, OP_MOVSX,
 OP MOVZX, OP MUL, OP NEG, OP NOP,
 OP_NOT, OP_OR, OP_OUT, OP_OUTSD,
 OP_OUTSW, OP_OUTSB, OP_PUSH, OP_PUSHAD,
 OP_PUSHFD, OP_POP, OP_POPAD, OP_POPFD,
 OP_RCL, OP_RCR, OP_RDMSR, OP_RDPMC,
 OP_RDTSC, OP_PREFIX_REPE, OP_PREFIX_REPNE, OP_RETF,
 OP_RETN, OP_ROL, OP_ROR, OP_RSM,
```

```
OP_SAHF, OP_SAR, OP_SBB, OP_SCASD,
 OP SCASW, OP SCASB, OP SETO, OP SETNO,
 OP_SETC, OP_SETNC, OP_SETZ, OP_SETNZ,
 OP SETBE, OP SETA, OP SETS, OP SETNS,
 OP_SETP, OP_SETNP, OP_SETL, OP_SETGE,
 OP SETLE, OP SETG, OP SGDT, OP SIDT,
 OP_SHL, OP_SHLD, OP_SHR, OP_SHRD,
 OP_SLDT, OP_STOSD, OP_STOSW, OP_STOSB,
 OP_STR, OP_STC, OP_STD, OP_STI,
 OP_SUB, OP_SYSCALL, OP_SYSENTER, OP_SYSEXIT,
 OP SYSRET, OP TEST, OP UD2, OP VERR,
 OP_VERRW, OP_WBINVD, OP_WRMSR, OP_XADD,
 OP_XCHG, OP_XLAT, OP_XOR, OP_FPU,
 OP F2XM1, OP FABS, OP FADD, OP FADDP,
 OP FBLD, OP FBSTP, OP FCHS, OP FCLEX,
 OP FCMOVB, OP FCMOVBE, OP FCMOVE, OP FCMOVNB,
 OP_FCMOVNBE, OP_FCMOVNE, OP_FCMOVNU, OP_FCMOVU,
 OP_FCOM, OP_FCOMI, OP_FCOMIP, OP_FCOMP,
 OP_FCOMPP, OP_FCOS, OP_FDECSTP, OP_FDIV,
 OP_FDIVP, OP_FDIVR, OP_FDIVRP, OP_FFREE,
 OP FIADD, OP FICOM, OP FICOMP, OP FIDIV,
 OP FIDIVR, OP FILD, OP FIMUL, OP FINCSTP,
 OP_FINIT, OP_FIST, OP_FISTP, OP_FISTTP,
 OP FISUB, OP FISUBR, OP FLD, OP FLD1,
 OP_FLDCW, OP_FLDENV, OP_FLDL2E, OP_FLDL2T,
 OP FLDLG2, OP FLDLN2, OP FLDPI, OP FLDZ,
 OP FMUL, OP FMULP, OP FNOP, OP FPATAN,
 OP_FPREM, OP_FPREM1, OP_FPTAN, OP_FRNDINT,
 OP FRSTOR, OP FSCALE, OP FSINCOS, OP FSQRT,
 OP_FSAVE, OP_FST, OP_FSTCW, OP_FSTENV,
 OP FSTP, OP FSTSW, OP FSUB, OP FSUBP,
 OP FSUBR, OP FSUBRP, OP FTST, OP FUCOM,
 OP_FUCOMI, OP_FUCOMIP, OP_FUCOMP, OP_FUCOMPP,
 OP_FXAM, OP_FXCH, OP_FXTRACT, OP_FYL2X,
 OP FYL2XP1 }
• enum DIS ACCESS {
 ACCESS NOARG, ACCESS IMM, ACCESS REL, ACCESS REG,
 ACCESS_MEM }
```

```
enum DIS_SIZE {
    SIZEB, SIZEW, SIZED, SIZEF,
    SIZEQ, SIZET, SIZEPTR }
```

\bullet enum X86REGS

7.3.2.1. Detailed Description

7.3.2.2. Enumeration Type Documentation

7.3.2.2.1. enum DIS_ACCESS Access type

Enumerator:

```
ACCESS\_NOARG arg not present ACCESS\_IMM immediate ACCESS\_REL +/- immediate ACCESS\_REG register ACCESS\_MEM [memory]
```

7.3.2.2.2. enum DIS_SIZE for mem access, immediate and relative

Enumerator:

```
SIZEB Byte size access SIZEW Word size access SIZED Doubleword size access SIZEF 6-byte access (seg+reg pair) SIZEQ Quadword access SIZET 10-byte access
```

7.3.2.2.3. enum X86OPS X86 opcode

SIZEPTR ptr

Enumerator:

```
OP_AAA Ascii Adjust after Addition
OP_AAD Ascii Adjust AX before Division
OP_AAM Ascii Adjust AX after Multiply
OP_AAS Ascii Adjust AL after Subtraction
OP_ADD Add
OP_ADC Add with Carry
OP_AND Logical And
OP_ARPL Adjust Requested Privilege Level
OP_BOUND Check Array Index Against Bounds
OP_BSF Bit Scan Forward
```

- OP_BSR Bit Scan Reverse
- OP_BSWAP Byte Swap
- OP_BT Bit Test
- OP_BTC Bit Test and Complement
- OP_BTR Bit Test and Reset
- OP BTS Bit Test and Set
- OP_CALL Call
- OP_CDQ Convert DoubleWord to QuadWord
- OP CWDE Convert Word to DoubleWord
- **OP_CBW** Convert Byte to Word
- OP_CLC Clear Carry Flag
- OP_CLD Clear Direction Flag
- OP_CLI Clear Interrupt Flag
- *OP_CLTS* Clear Task-Switched Flag in CR0
- OP_CMC Complement Carry Flag
- OP_CMOVO Conditional Move if Overflow
- OP CMOVNO Conditional Move if Not Overflow
- OP CMOVC Conditional Move if Carry
- *OP_CMOVNC* Conditional Move if Not Carry
- OP_CMOVZ Conditional Move if Zero
- OP_CMOVNZ Conditional Move if Non-Zero
- OP_CMOVBE Conditional Move if Below or Equal
- OP_CMOVA Conditional Move if Above
- *OP_CMOVS* Conditional Move if Sign
- OP_CMOVNS Conditional Move if Not Sign
- *OP_CMOVP* Conditional Move if Parity
- OP_CMOVNP Conditional Move if Not Parity
- OP_CMOVL Conditional Move if Less
- OP_CMOVGE Conditional Move if Greater or Equal
- OP_CMOVLE Conditional Move if Less than or Equal
- OP_CMOVG Conditional Move if Greater
- OP_CMP Compare
- *OP_CMPSD* Compare String DoubleWord
- OP_CMPSW Compare String Word
- *OP_CMPSB* Compare String Byte
- OP CMPXCHG Compare and Exchange
- *OP_CMPXCHG8B* Compare and Exchange Bytes
- OP_CPUID CPU Identification

- OP_DAA Decimal Adjust AL after Addition
- OP_DAS Decimal Adjust AL after Subtraction
- OP_DEC Decrement by 1
- **OP_DIV** Unsigned Divide
- **OP_ENTER** Make Stack Frame for Procedure Parameters
- **OP FWAIT** Wait
- OP_HLT Halt
- OP_IDIV Signed Divide
- OP_IMUL Signed Multiply
- **OP_INC** Increment by 1
- **OP_IN** INput from port
- OP_INSD INput from port to String Doubleword
- OP_INSW INput from port to String Word
- OP_INSB INput from port to String Byte
- **OP_INT** INTerrupt
- *OP_INT3* INTerrupt 3 (breakpoint)
- OP_INTO INTerrupt 4 if Overflow
- OP INVD Invalidate Internal Caches
- OP_INVLPG Invalidate TLB Entry
- OP_IRET Interrupt Return
- OP_JO Jump if Overflow
- **OP_JNO** Jump if Not Overflow
- **OP_JC** Jump if Carry
- **OP_JNC** Jump if Not Carry
- OP_JZ Jump if Zero
- OP_JNZ Jump if Not Zero
- **OP JBE** Jump if Below or Equal
- **OP_JA** Jump if Above
- OP_JS Jump if Sign
- OP_JNS Jump if Not Sign
- OP_JP Jump if Parity
- OP_JNP Jump if Not Parity
- OP_JL Jump if Less
- **OP_JGE** Jump if Greater or Equal
- OP_JLE Jump if Less or Equal
- $OP \ JG$ Jump if Greater
- OP_JMP Jump (unconditional)
- OP_LAHF Load Status Flags into AH Register

- OP_LAR load Access Rights Byte
- OP_LDS Load Far Pointer into DS
- OP_LES Load Far Pointer into ES
- OP_LFS Load Far Pointer into FS
- OP_LGS Load Far Pointer into GS
- OP LEA Load Effective Address
- OP_LEAVE High Level Procedure Exit
- OP_LGDT Load Global Descript Table Register
- OP_LIDT Load Interrupt Descriptor Table Register
- *OP_LLDT* Load Local Descriptor Table Register
- OP_PREFIX_LOCK Assert LOCK# Signal Prefix
- OP_LODSD Load String Dword
- OP_LODSW Load String Word
- *OP_LODSB* Load String Byte
- OP_LOOP Loop According to ECX Counter
- OP_LOOPE Loop According to ECX Counter and ZF=1
- *OP_LOOPNE* Looop According to ECX Counter and ZF=0
- OP_JECXZ Jump if ECX is Zero
- OP_LSL Load Segment Limit
- OP_LSS Load Far Pointer into SS
- OP_LTR Load Task Register
- **OP_MOV** Move
- OP_MOVSD Move Data from String to String Doubleword
- OP_MOVSW Move Data from String to String Word
- *OP_MOVSB* Move Data from String to String Byte
- *OP_MOVSX* Move with Sign-Extension
- OP_MOVZX Move with Zero-Extension
- **OP_MUL** Unsigned Multiply
- **OP_NEG** Two's Complement Negation
- **OP_NOP** No Operation
- OP_NOT One's Complement Negation
- OP_OR Logical Inclusive OR
- *OP_OUT* Output to Port
- OP OUTSD Output String to Port Doubleword
- OP_OUTSW Output String to Port Word
- OP OUTSB Output String to Port Bytes
- OP_PUSH Push Onto the Stack
- OP_PUSHAD Push All Double General Purpose Registers

- OP_PUSHFD Push EFLAGS Register onto the Stack
- OP_POP Pop a Value from the Stack
- OP_POPAD Pop All Double General Purpose Registers from the Stack
- OP_POPFD Pop Stack into EFLAGS Register
- OP_RCL Rotate Carry Left
- OP_RCR Rotate Carry Right
- OP_RDMSR Read from Model Specific Register
- *OP_RDPMC* Read Performance Monitoring Counters
- OP_RDTSC Read Time-Stamp Coutner
- OP_PREFIX_REPE Repeat String Operation Prefix while Equal
- OP_PREFIX_REPNE Repeat String Operation Prefix while Not Equal
- **OP_RETF** Return from Far Procedure
- OP RETN Return from Near Procedure
- OP_ROL Rotate Left
- OP_ROR Rotate Right
- OP_RSM Resumse from System Management Mode
- OP_SAHF Store AH into Flags
- OP SAR Shift Arithmetic Right
- OP_SBB Subtract with Borrow
- OP_SCASD Scan String Doubleword
- OP_SCASW Scan String Word
- OP_SCASB Scan String Byte
- OP_SETO Set Byte on Overflow
- **OP_SETNO** Set Byte on Not Overflow
- OP_SETC Set Byte on Carry
- **OP_SETNC** Set Byte on Not Carry
- OP SETZ Set Byte on Zero
- OP_SETNZ Set Byte on Not Zero
- **OP_SETBE** Set Byte on Below or Equal
- **OP_SETA** Set Byte on Above
- OP_SETS Set Byte on Sign
- $\boldsymbol{OP_SETNS}$ Set Byte on Not Sign
- **OP_SETP** Set Byte on Parity
- OP SETNP Set Byte on Not Parity
- *OP_SETL* Set Byte on Less
- OP SETGE Set Byte on Greater or Equal
- OP_SETLE Set Byte on Less or Equal
- OP_SETG Set Byte on Greater

- OP_SGDT Store Global Descriptor Table Register
- OP_SIDT Store Interrupt Descriptor Table Register
- OP_SHL Shift Left
- OP_SHLD Double Precision Shift Left
- OP_SHR Shift Right
- OP_SHRD Double Precision Shift Right
- OP_SLDT Store Local Descriptor Table Register
- OP_STOSD Store String Doubleword
- OP_STOSW Store String Word
- OP_STOSB Store String Byte
- OP_STR Store Task Register
- OP_STC Set Carry Flag
- OP_STD Set Direction Flag
- OP_STI Set Interrupt Flag
- OP_SUB Subtract
- OP_SYSCALL Fast System Call
- OP_SYSENTER Fast System Call
- OP SYSEXIT Fast Return from Fast System Call
- OP_SYSRET Return from Fast System Call
- **OP_TEST** Logical Compare
- OP_UD2 Undefined Instruction
- OP_VERR Verify a Segment for Reading
- OP_VERRW Verify a Segment for Writing
- OP_WBINVD Write Back and Invalidate Cache
- OP_WRMSR Write to Model Specific Register
- **OP_XADD** Exchange and Add
- OP_XCHG Exchange Register/Memory with Register
- OP_XLAT Table Look-up Translation
- OP_XOR Logical Exclusive OR
- OP_FPU FPU operation
- **OP_F2XM1** Compute 2x-1
- OP_FABS Absolute Value
- *OP_FADD* Floating Point Add
- OP_FADDP Floating Point Add, Pop
- OP_FBLD Load Binary Coded Decimal
- OP FBSTP Store BCD Integer and Pop
- OP_FCHS Change Sign
- OP_FCLEX Clear Exceptions

- OP_FCMOVB Floating Point Move on Below
- OP_FCMOVBE Floating Point Move on Below or Equal
- OP_FCMOVE Floating Point Move on Equal
- OP_FCMOVNB Floating Point Move on Not Below
- OP_FCMOVNBE Floating Point Move on Not Below or Equal
- OP_FCMOVNE Floating Point Move on Not Equal
- $OP_FCMOVNU$ Floating Point Move on Not Unordered
- OP_FCMOVU Floating Point Move on Unordered
- OP_FCOM Compare Floating Pointer Values and Set FPU Flags
- OP_FCOMI Compare Floating Pointer Values and Set EFLAGS
- OP_FCOMIP Compare Floating Pointer Values and Set EFLAGS, Pop
- OP_FCOMP Compare Floating Pointer Values and Set FPU Flags, Pop
- OP_FCOMPP Compare Floating Pointer Values and Set FPU Flags, Pop Twice
- OP_FCOS Cosine
- $OP_FDECSTP$ Decrement Stack Top Pointer
- **OP_FDIV** Floating Point Divide
- OP_FDIVP Floating Point Divide, Pop
- OP_FDIVR Floating Point Reverse Divide
- OP_FDIVRP Floating Point Reverse Divide, Pop
- *OP_FFREE* Free Floating Point Register
- OP_FIADD Floating Point Add
- OP_FICOM Compare Integer
- OP_FICOMP Compare Integer, Pop
- *OP_FIDIV* Floating Point Divide by Integer
- OP_FIDIVR Floating Point Reverse Divide by Integer
- **OP_FILD** Load Integer
- OP_FIMUL Floating Point Multiply with Integer
- OP_FINCSTP Increment Stack-Top Pointer
- **OP_FINIT** Initialize Floating-Point Unit
- OP_FIST Store Integer
- OP_FISTP Store Integer, Pop
- OP_FISTTP Store Integer with Truncation
- *OP_FISUB* Floating Point Integer Subtract
- *OP_FISUBR* Floating Point Reverse Integer Subtract
- *OP_FLD* Load Floating Point Value
- OP FLD1 Load Constant 1
- OP_FLDCW Load x87 FPU Control Word
- OP_FLDENV Load x87 FPU Environment

- *OP_FLDL2E* Load Constant log_2(e)
- OP_FLDL2T Load Constant log_2(10)
- OP_FLDLG2 Load Constant log_10(2)
- OP_FLDLN2 Load Constant log e(2)
- OP_FLDPI Load Constant PI
- OP_FLDZ Load Constant Zero
- **OP_FMUL** Floating Point Multiply
- **OP_FMULP** Floating Point Multiply, Pop
- OP_FNOP No Operation
- OP_FPATAN Partial Arctangent
- OP_FPREM Partial Remainder
- OP_FPREM1 Partial Remainder
- OP_FPTAN Partial Tangent
- $OP_FRNDINT$ Round to Integer
- OP_FRSTOR Restore x86 FPU State
- OP_FSCALE Scale
- OP_FSINCOS Sine and Cosine
- OP_FSQRT Square Root
- OP FSAVE Store x87 FPU State
- OP_FST Store Floating Point Value
- OP_FSTCW Store x87 FPU Control Word
- OP_FSTENV Store x87 FPU Environment
- OP_FSTP Store Floating Point Value, Pop
- OP_FSTSW Store x87 FPU Status Word
- OP_FSUB Floating Point Subtract
- OP FSUBP Floating Point Subtract, Pop
- OP_FSUBR Floating Point Reverse Subtract
- OP_FSUBRP Floating Point Reverse Subtract, Pop
- OP_FTST Floating Point Test
- OP FUCOM Floating Point Unordered Compare
- OP_FUCOMI Floating Point Unordered Compare with Integer
- OP_FUCOMIP Floating Point Unorder Compare with Integer, Pop
- OP_FUCOMP Floating Point Unorder Compare, Pop
- *OP_FUCOMPP* Floating Point Unorder Compare, Pop Twice
- **OP FXAM** Examine ModR/M
- *OP_FXCH* Exchange Register Contents
- OP_FXTRACT Extract Exponent and Significand
- OP FYL2X Compute v*log2x
- $OP_FYL2XP1$ Compute y*log2(x+1)

7.3.2.2.4. enum X86REGS X86 registers

7.3.3. bytecode execs.h File Reference

Data Structures

- struct cli exe section
- struct cli_exe_info

7.3.3.1. Detailed Description

7.3.4. bytecode_pe.h File Reference

Data Structures

- struct pe image file hdr
- struct pe_image_data_dir
- struct pe_image_optional_hdr32
- struct pe_image_optional_hdr64
- struct pe image section hdr
- struct cli_pe_hook_data

7.3.4.1. Detailed Description

7.4. High level API

7.4.1. bytecode_local.h File Reference

Data Structures

- struct DIS mem arg
- struct DIS_arg
- struct DIS fixed

Defines

- $\bullet \ \ \# define \ VIRUSNAME_PREFIX (name) \ const \ char \ __clambc_virusname_prefix[] = name;$
- #define VIRUSNAMES(...) const char *const __clambc_virusnames[] = {___VA_ARGS_-__};
- #define PE_UNPACKER_DECLARE const uint16_t ___clambc_kind = BC_PE_-UNPACKER;
- #define PDF_HOOK_DECLARE const uint16_t __clambc_kind = BC_PDF;
- #define BYTECODE_ABORT_HOOK 0xcea5e
- #define PE_HOOK_DECLARE const uint16_t __clambc_kind = BC_PE_ALL;
- #define SIGNATURES DECL BEGIN struct Signatures {
- #define DECLARE_SIGNATURE(name)
- #define SIGNATURES_DECL_END };
- #define TARGET(tgt) const unsigned short ___Target = (tgt);
- #define COPYRIGHT(c) const char *const ___Copyright = (c);

7.4. High level API

- #define ICONGROUP1(group) const char *const ___IconGroup1 = (group);
- #define ICONGROUP2(group) const char *const ___IconGroup2 = (group);
- #define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short ___FuncMin = (m);
- #define FUNCTIONALITY_LEVEL_MAX(m) const unsigned short ___FuncMax = (m);
- #define SIGNATURES_DEF_BEGIN
- #define DEFINE_SIGNATURE(name, hex)
- #define SIGNATURES END \};\

Functions

- static force inline void overloadable func debug (const char *str)
- static force inline void overloadable func debug (const uint8 t *str)
- static force_inline void overloadable_func debug (uint32_t a)
- void debug (...) __attribute__((overloadable
- static force_inline uint32_t count_match (___Signature sig)
- static force_inline uint32_t matches (___Signature sig)
- static force_inline uint32_t match_location (___Signature sig, uint32_t goback)
- static force_inline int32_t match_location_check (__Signature sig, uint32_t goback, const char *static_start, uint32_t static_len)
- static force_inline overloadable_func void foundVirus (const char *virusname)
- static force inline void overloadable func foundVirus (void)
- static force_inline uint32_t getFilesize (void)
- bool __is_bigendian (void) __attribute__((const)) __attribute__((nothrow))
- static uint32_t force_inline le32_to_host (uint32_t v)
- static uint64_t force_inline le64_to_host (uint64_t v)
- static uint 16_t force_inline le
16_to_host (uint 16_t v)
- static uint32_t force_inline cli_readint32 (const void *buff)
- static uint16_t force_inline cli_readint16 (const void *buff)
- static void force_inline cli_writeint32 (void *offset, uint32_t v)
- static force inline bool hasExeInfo (void)
- static force_inline bool hasPEInfo (void)
- static force inline bool is PE64 (void)
- static static force_inline force_inline uint8_t getPEMajorLinkerVersion (void)
- static force_inline uint8_t getPEMinorLinkerVersion (void)
- static force_inline uint32_t getPESizeOfCode (void)
- static force_inline uint32_t getPESizeOfInitializedData (void)
- static force inline uint32 t getPESizeOfUninitializedData (void)
- static force inline uint32 t getPEBaseOfCode (void)
- static force inline uint32 t getPEBaseOfData (void)
- static force_inline uint64_t getPEImageBase (void)
- static force inline uint32 t getPESectionAlignment (void)
- static force inline uint32 t getPEFileAlignment (void)
- static force inline uint16 t getPEMajorOperatingSystemVersion (void)
- static force_inline uint16_t getPEMinorOperatingSystemVersion (void)
- static force_inline uint16_t getPEMajorImageVersion (void)
- static force_inline uint16_t getPEMinorImageVersion (void)

uint32 t len)

- static force_inline uint 16_t getPEMajorSubsystemVersion (void) • static force_inline uint16_t getPEMinorSubsystemVersion (void) static force inline uint32 t getPEWin32VersionValue (void) • static force inline uint32 t getPESizeOfImage (void) • static force_inline uint32_t getPESizeOfHeaders (void) static force_inline uint32_t getPECheckSum (void) static force inline uint16 t getPESubsystem (void) static force inline uint16 t getPEDllCharacteristics (void) Return the PE DllCharacteristics. • static force_inline uint32_t getPESizeOfStackReserve (void) static force_inline uint32_t getPESizeOfStackCommit (void) static force inline uint32 t getPESizeOfHeapReserve (void) static force inline uint32 t getPESizeOfHeapCommit (void) static force_inline uint32_t getPELoaderFlags (void) static force inline uint16 t getPEMachine () static force_inline uint32_t getPETimeDateStamp () static force inline uint32 t getPEPointerToSymbolTable () static force inline uint32 t getPENumberOfSymbols () static force inline uint16 t getPESizeOfOptionalHeader () static force inline uint16 t getPECharacteristics () static force_inline bool getPEisDLL () static force_inline uint32_t getPEDataDirRVA (unsigned n) • static force inline uint32 t getPEDataDirSize (unsigned n) static force inline uint16 t getNumberOfSections (void) static uint32_t getPELFANew (void) static force inline int readPESectionName (unsigned char name[8], unsigned n) static force_inline uint32_t getEntryPoint (void) static force inline uint32 t getExeOffset (void) static force_inline uint32_t getImageBase (void) static uint32 t getVirtualEntryPoint (void) static uint32 t getSectionRVA (unsigned i) static uint32_t getSectionVirtualSize (unsigned i) • static force_inline bool readRVA (uint32_t rva, void *buf, size_t bufsize) static void * memchr (const void *s, int c, size t n) void * memset (void *src, int c, uintptr_t n) __attribute__((nothrow)) __attribute__- $((\underline{\hspace{1cm}} nonnull \underline{\hspace{1cm}} ((1)))$ void * memmove (void *dst, const void *src, uintptr_t n) __attribute__((__nothrow___)) $_{\text{attribute}}$ $((\underline{\hspace{0.2cm}}$ nonnull $\underline{\hspace{0.2cm}}$ (1• void *void memcpy (void *restrict dst, const void *restrict src, uintptr_t n) __attribute_-__((___nothrow___)) ___attribute___((___nonnull___(1 • void *void int memcmp (const void *s1, const void *s2, uint32 t n) attribute ((nothrow___)) __attribute__((__pure___)) __attribute__((__nonnull___(1

• static int32_t ilog2_compat (uint32_t a, uint32_t b)

static force inline uint32 t DisassembleAt (struct DIS fixed *result, uint32 t offset,

7.4. High level API

7.4.1.1. Detailed Description

7.4.1.2. Define Documentation

7.4.1.2.1. #define BYTECODE_ABORT_HOOK 0xcea5e entrypoint() return code that tells hook invoker that it should skip executing, probably because it'd trigger a bug in it

7.4.1.2.2. #define COPYRIGHT(c) const char *const ___Copyright = (c); Defines an alternative copyright for this bytecode.

config

This will also prevent the sourcecode from being embedded into the bytecode

7.4.1.2.3. #define DECLARE_SIGNATURE(name) Value:

```
const char *name##_sig;\
    __Signature name;
```

Declares a name for a subsignature.

config

7.4.1.2.4. #define DEFINE_SIGNATURE(name, hex) Value:

```
.name##_sig = (hex),\
    .name = {__COUNTER__ - __signature_bias},
```

Defines the pattern for a previously declared subsignature.

See also

DECLARE SIGNATURE

config

Parameters

name	the name of a previously declared subsignature
hex	the pattern for this subsignature

7.4.1.2.5. #define FUNCTIONALITY_LEVEL_MAX(m) const unsigned short ___FuncMax = (m); Define the maximum engine functionality level required for this byte-code/logical signature. Engines newer than this will skip loading the bytecode. You can use the 'enum FunctionalityLevels' constants here.

config

7.4.1.2.6. #define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short ___FuncMin = (m); Define the minimum engine functionality level required for this byte-code/logical signature. Engines older than this will skip loading the bytecode. You can use the

 ${\rm `enum\ Functionality Levels'\ constants\ here}.$

config

7.4.1.2.7. #define ICONGROUP1(group) const char *const ___IconGroup1 = (group); Define IconGroup1 for logical signature. See logical signature documentation for what it is

config

7.4.1.2.8. #define ICONGROUP2(group) const char *const ___IconGroup2 = (group); Define IconGroup2 for logical signature. See logical signature documentation for what it is.

config

7.4.1.2.9. #define PDF_HOOK_DECLARE const uint16_t ___clambc_kind = BC_-PDF; Make the current bytecode a PDF hook. Having a logical signature doesn't make sense here, since logical signature is evaluated AFTER these hooks run.

config

This hook is called several times, use pdf_get_phase() to find out in which phase you got called.

7.4.1.2.10. #define PE_HOOK_DECLARE const uint16_t __clambc_kind = BC_-PE_ALL; Make the current bytecode a PE hook, i.e. it will be called once the logical signature trigger matches (or always if there is none), and you have access to all the PE information. By default you only have access to execs.h information, and not to PE field information (even for PE files).

config

7.4.1.2.11. #define PE_UNPACKER_DECLARE const uint16_t __clambc_kind = BC_PE_UNPACKER; Like PE_HOOK_DECLARE, but it is not run for packed files that pe.c can unpack (only on the unpacked file).

config

 $7.4.1.2.12. \ \# define \ SIGNATURES_DECL_BEGIN \ struct \ __Signatures \ \{ \ \ Marks \ the \ beginning \ of \ the \ subsignature \ name \ declaration \ section.$

config

7.4. High level API

7.4.1.2.13. #define SIGNATURES_DECL_END }; Marks the end of the subsignature name declaration section.

config

```
7.4.1.2.14. #define SIGNATURES_DEF_BEGIN Value:
```

```
static const unsigned __signature_bias = __COUNTER__+1;\
const struct __Signatures Signatures = {\
```

Marks the beginning of subsignature pattern definitions.

config

See also

```
SIGNATURES_DECL_BEGIN
```

7.4.1.2.15. #define SIGNATURES_END $\}$;\ Marks the end of the subsignature pattern definitions.

config

7.4.1.2.16. #define TARGET(tgt) const unsigned short ___Target = (tgt); Defines the ClamAV file target.

config

Parameters

```
tgt | ClamAV signature type (0 - raw, 1 - PE, etc.)
```

7.4.1.2.17. #define VIRUSNAME_PREFIX(name) const char ___clambc_-virusname_prefix[] = name; Declares the virusname prefix.

config

Parameters

name the prefix common to all viruses reported by this bytecode

 $7.4.1.2.18. \ \# define \ VIRUSNAMES(\ \dots \) \ const \ char *const __clambc_virusnames[] \\ = \{ __VA_ARGS__ \}; \ \ Declares \ all \ the \ virusnames \ that \ this \ bytecode \ can \ report.$

config

Parameters

... a comma-separated list of strings interpreted as virusnames

7.4.1.3. Function Documentation

7.4.1.3.1. bool ___is_bigendian (void) const Returns true if the bytecode is executing on a big-endian CPU.

Returns

true if executing on bigendian CPU, false otherwise

Environment

This will be optimized away in libclamay, but it must be used when dealing with endianess for portability reasons. For example whenever you read a 32-bit integer from a file, it can be written in little-endian convention (x86 CPU for example), or big-endian convention (PowerPC CPU for example). If the file always contains little-endian integers, then conversion might be needed. ClamAV bytecodes by their nature must only handle known-endian integers, if endianness can change, then both situations must be taken into account (based on a 1-byte field for example).

7.4.1.3.2. static uint 16_t force_inline cli_readint 16 (const void * buff) [static] Reads from the specified buffer a 16-bit of little-endian integer.

Data structure

Parameters

in buff pointer to buffer

Returns

16-bit little-endian integer converted to host endianness

7.4.1.3.3. static uint32_t force_inline cli_readint32 (const void * buff) [static] Reads from the specified buffer a 32-bit of little-endian integer.

Data structure

Parameters

in	buff	pointer to buffer

Returns

32-bit little-endian integer converted to host endianness

7.4.1.3.4. static void force_inline cli_writeint32 (void * offset, uint32_t v) [static] Writes the specified value into the specified buffer in little-endian order

90 7.4. High level API

Data structure

Parameters

out	offset	pointer to buffer to write to
in	v	value to write

7.4.1.3.5. static force_inline uint32_t count_match (___Signature sig) [static] Returns how many times the specified signature matched.

Parameters

sig	name of subsignature queried

Returns

number of times this subsignature matched in the entire file

Engine query

This is a constant-time operation, the counts for all subsignatures are already computed.

7.4.1.3.6. void debug (...) debug is an overloaded function (yes clang supports that in C!), but it only works on strings, and integers. Give an error on any other type

7.4.1.3.7. static force_inline void overloadable_func debug (const char * str) [static] Prints str to clamscan's --debug output.

Parameters

str	null terminated string

7.4.1.3.8. static force_inline void overloadable_func debug (const uint8_t * str) [static] Prints str to clamscan's --debug output.

Parameters

str	null terminated string

7.4.1.3.9. static force_inline void overloadable_func debug (uint32_t a) [static] Prints a integer to clamscan's --debug output.

Parameters

a integer	
-----------	--

Disassemble

Parameters

out	result	disassembly result
in	offset	start disassembling from this offset, in the current file
in	len	max amount of bytes to disassemble

Returns

offset where disassembly ended

7.4.1.3.11. static force_inline overloadable_func void foundVirus (const char * virusname) [static] Sets the specified virusname as the virus detected by this byte-code.

Scan

Parameters

virusname	the name of the virus, excluding the prefix, must be one of the virusnames declared
	in VIRUSNAMES.

See also

VIRUSNAMES

7.4.1.3.12. static force_inline void overloadable_func foundVirus (void) [static] Like foundVirus() but just use the prefix as virusname

7.4.1.3.13. static force_inline uint32_t getEntryPoint (void) [static] Returns the offset of the EntryPoint in the executable file.

 \mathbf{PE}

Returns

offset of EP as 32-bit unsigned integer

 $7.4.1.3.14. \ static \ force_inline \ uint 32_t \ getExeOffset \ (\ void \) \ [static] \ \ Returns the offset of the executable in the file.$

 \mathbf{PE}

Returns

offset of embedded executable inside file.

 $7.4.1.3.15.\ static\ force_inline\ uint 32_t\ getFilesize\ (\ void\)\ [static]\ \ Returns\ the$ currently scanned file's size.

File operation

92 7.4. High level API

Returns

file size as 32-bit unsigned integer

7.4.1.3.16. static force_inline uint32_t getImageBase (void) [static] Returns the ImageBase with the correct endian conversion. Only works if the bytecode is a PE hook (i.e. you invoked PE_UNPACKER_DECLARE)

 \mathbf{PE}

Returns

ImageBase of PE file, 0 - for non-PE hook

7.4.1.3.17. static force_inline uint16_t getNumberOfSections (void) [static] Returns the number of sections in this executable file.

 \mathbf{PE}

Returns

number of sections as 16-bit unsigned integer

 $7.4.1.3.18.\ static\ force_inline\ uint32_t\ getPEBaseOfCode\ (\ void\)\ [static] \ \ Return\ the\ PE\ BaseOfCode.$

 \mathbf{PE}

Returns

PE BaseOfCode, or 0 if not in PE hook.

 $7.4.1.3.19.\ static \ force_inline \ uint 32_t \ get PEBase Of Data (void) \ [static]$ Return the PE Base Of Data.

 \mathbf{PE}

Returns

PE BaseOfData, or 0 if not in PE hook.

7.4.1.3.20. static force_inline uint16_t getPECharacteristics () [static] Returns PE characteristics. For example you can use this to check whether it is a DLL (0x2000).

 \mathbf{PE}

Returns

characteristic of PE file, or 0 if not in PE hook

 $7.4.1.3.21.\ static\ force_inline\ uint 32_t\ get PECheck Sum\ (\ void\)\ [static] \ Return\ the\ PE\ Check Sum.$

 \mathbf{PE}

Returns

PE CheckSum, or 0 if not in PE hook

7.4.1.3.22. static force_inline uint32_t getPEDataDirRVA (unsigned n) [static] Gets the virtual address of specified image data directory.

 \mathbf{PE}

Parameters

n image directory requested

Returns

Virtual Address of requested image directory

7.4.1.3.23. static force_inline uint32_t getPEDataDirSize (unsigned n) [static] Gets the size of the specified image data directory.

 \mathbf{PE}

Parameters

n image directory requested

Returns

Size of requested image directory

 $7.4.1.3.24.\ static\ force_inline\ uint16_t\ getPEDllCharacteristics\ (\ void\)\ [static]$ Return the PE DllCharacteristics.

 \mathbf{PE}

Returns

PE DllCharacteristics, or 0 if not in PE hook

7.4.1.3.25. static force_inline uint32_t getPEFileAlignment (void) [static] Return the PE FileAlignment.

 \mathbf{PE}

Returns

PE FileAlignment, or 0 if not in PE hook

94 7.4. High level API

7.4.1.3.26. static force_inline uint64_t getPEImageBase (void) [static] Return the PE ImageBase as 64-bit integer.

 \mathbf{PE}

Returns

PE ImageBase as 64-bit int, or 0 if not in PE hook

 $7.4.1.3.27. \ static \ force_inline \ bool \ getPEisDLL \ (\ \) \ \ [static] \ \ Returns \ whether \ this is a \ DLL. \ Use \ this \ only \ in \ a \ PE \ hook!$

 \mathbf{PE}

Returns

true - the file is a DLL false - file is not a DLL

 \mathbf{PE}

Returns

offset to the PE header, or 0 if not in PE hook

 $7.4.1.3.29.\ static \ force_inline \ uint 32_t \ get PELoader Flags (void) [static] Return the PE Loader Flags.$

 \mathbf{PE}

Returns

PE LoaderFlags or 0 if not in PE hook

 $7.4.1.3.30. \ \ static \ \ force_inline \ \ uint16_t \ \ getPEMachine \ (\ \) \ \ [static] \ \ Returns \ the CPU \ this executable runs on, see libclamav/pe.c for possible values.$

 \mathbf{PE}

Returns

PE Machine or 0 if not in PE hook

7.4.1.3.31. static force_inline uint 16_t getPEMajorImageVersion (void) [static] Return the PE MajorImageVersion.

 \mathbf{PE}

Returns

PE MajorImageVersion, or 0 if not in PE hook

7.4.1.3.32. static static force_inline force_inline uint8_t getPEMajorLinkerVersion (void) [static] Returns MajorLinkerVersion for this PE file.

PE

Returns

PE MajorLinkerVersion or 0 if not in PE hook

7.4.1.3.33. static force_inline uint16_t getPEMajorOperatingSystemVersion (void) [static] Return the PE MajorOperatingSystemVersion.

PE

Returns

PE MajorOperatingSystemVersion, or 0 if not in PE hook

7.4.1.3.34. static force_inline uint16_t getPEMajorSubsystemVersion (void) [static] Return the PE MajorSubsystemVersion.

PE

Returns

PE MajorSubsystemVersion or 0 if not in PE hook

 $7.4.1.3.35.\ static\ force_inline\ uint 16_t\ get PEMinorImageVersion\ (\ void\)\ \ [static]$ Return the PE MinorImageVersion.

 \mathbf{PE}

Returns

PE MinorrImageVersion, or 0 if not in PE hook

7.4.1.3.36. static force_inline uint8_t getPEMinorLinkerVersion (void) [static] Returns MinorLinkerVersion for this PE file. PE

Returns

PE MinorLinkerVersion or 0 if not in PE hook

7.4.1.3.37. static force_inline uint16_t getPEMinorOperatingSystemVersion (void) [static] Return the PE MinorOperatingSystemVersion.

PE

Returns

PE MinorOperatingSystemVersion, or 0 if not in PE hook

96 7.4. High level API

7.4.1.3.38. static force_inline uint16_t getPEMinorSubsystemVersion (void | [static] Return the PE MinorSubsystemVersion.

PE

Returns

PE MinorSubsystemVersion, or 0 if not in PE hook

7.4.1.3.39. static force_inline uint32_t getPENumberOfSymbols () [static] Returns the PE number of debug symbols PE

Returns

PE NumberOfSymbols or 0 if not in PE hook

7.4.1.3.40. static force_inline uint32_t getPEPointerToSymbolTable () [static] Returns pointer to the PE debug symbol table PE

Returns

PE PointerToSymbolTable or 0 if not in PE hook

7.4.1.3.41. static force_inline uint32_t getPESectionAlignment (void) [static] Return the PE SectionAlignment. PE

Returns

PE SectionAlignment, or 0 if not in PE hook

7.4.1.3.42. static force_inline uint32_t get PESizeOfCode (void) [static] Return the PE SizeOfCode. PE

Returns

PE SizeOfCode or 0 if not in PE hook

7.4.1.3.43. static force_inline uint32_t getPESizeOfHeaders (void) [static] Return the PE SizeOfHeaders. PE

Returns

PE SizeOfHeaders, or 0 if not in PE hook

 $7.4.1.3.44.\ static\ force_inline\ uint 32_t\ get PESize Of Heap Commit\ (\ void\)\ [static]$ Return the PE Size Of Heap Commit.

PE

Returns

PE SizeOfHeapCommit, or 0 if not in PE hook

7.4.1.3.45. static force_inline uint32_t getPESizeOfHeapReserve (void) [static] Return the PE SizeOfHeapReserve.

PE

Returns

PE SizeOfHeapReserve, or 0 if not in PE hook

 $\label{eq:continuous} \textbf{7.4.1.3.46. static force_inline uint32_t getPESizeOfImage (void) [static]} \quad \text{Return the PE SizeOfImage}.$

PE

Returns

PE SizeOfImage, or 0 if not in PE hook

 $7.4.1.3.47.\ static\ force_inline\ uint 32_t\ get PESize Of Initialized Data\ (\ void\)\ \ [static]$ Return the PE Size of Initialized Data.

 \mathbf{PE}

Returns

PE SizeOfInitializeData or 0 if not in PE hook

7.4.1.3.48. static force_inline uint16_t getPESizeOfOptionalHeader () [static] Returns the size of PE optional header.

 \mathbf{PE}

Returns

size of PE optional header, or 0 if not in PE hook

 $7.4.1.3.49.\ static\ force_inline\ uint 32_t\ get PESize Of Stack Commit\ (\ void\)\ [static]$ Return the PE Size Of Stack Commit.

PE

Returns

PE SizeOfStackCommit, or 0 if not in PE hook

98 7.4. High level API

 $7.4.1.3.50.\ static\ force_inline\ uint 32_t\ get PESize Of Stack Reserve\ (\ void\)\ [static]$ Return the PE Size Of Stack Reserve.

PE

Returns

PE SizeOfStackReserver, or 0 if not in PE hook

 \mathbf{PE}

Returns

PE SizeofUninitializedData or 0 if not in PE hook

7.4.1.3.52. static force_inline uint16_t getPESubsystem (void) [static] Return the PE Subsystem.

 \mathbf{PE}

Returns

PE subsystem, or 0 if not in PE hook

 $7.4.1.3.53.\ static\ force_inline\ uint 32_t\ get PET ime Date Stamp\ (\quad \)\ \ [static] \ \ Returns\ the\ PE\ Time Date Stamp\ from\ headers$

 \mathbf{PE}

Returns

PE TimeDateStamp or 0 if not in PE hook

 $7.4.1.3.54.\ static\ force_inline\ uint 32_t\ get PEW in 32 Version Value\ (\ void\)\ [static]$ Return the PE Win 32 Version Value.

 \mathbf{PE}

Returns

PE Win32VersionValue, or 0 if not in PE hook

7.4.1.3.55. static uint32_t getSectionRVA (unsigned i) [static] Return the RVA of the specified section

 \mathbf{PE}

Parameters

i section index (from 0)

Returns

RVA of section, or -1 if invalid

7.4.1.3.56. static uint32_t getSectionVirtualSize (unsigned i) [static] Return the virtual size of the specified section.

 \mathbf{PE}

Parameters

i section index (from 0)

Returns

VSZ of section, or -1 if invalid

7.4.1.3.57. static uint32_t getVirtualEntryPoint (void) [static] The address of the EntryPoint. Use this for matching EP against sections.

 \mathbf{PE}

Returns

virtual address of EntryPoint, or 0 if not in PE hook

7.4.1.3.58. static force_inline bool hasExeInfo (void) [static] Returns whether the current file has executable information.

 \mathbf{PE}

Returns

true if the file has exe info, false otherwise

7.4.1.3.59. static force_inline bool hasPEInfo (void) [static] Returns whether PE information is available

 \mathbf{PE}

Returns

true if PE information is available (in PE hooks)

7.4. High level API

7.4.1.3.60. static int32_t ilog2_compat (uint32_t a, uint32_t b) [inline, static] ilog2_compat for 0.96 compatibility, you should use ilog2() 0.96.1 API instead of this one!

7.4.1.3.61. static force_inline bool isPE64 (void) [static] Returns whether this is a PE32+ executable.

 \mathbf{PE}

Returns

true if this is a PE32+ executable

7.4.1.3.62. static uint16_t force_inline le16_to_host (uint16_t v) [static] Converts the specified value if needed, knowing it is in little endian order.

Data structure

Parameters

in v 16-bit integer as read from a file	
---	--

Returns

integer converted to host's endianess

7.4.1.3.63. static uint32_t force_inline le32_to_host (uint32_t v) [static] Converts the specified value if needed, knowing it is in little endian order.

Data structure

Parameters

in	v	32-bit integer as read from a file
----	---	------------------------------------

Returns

integer converted to host's endianess

7.4.1.3.64. static uint64_t force_inline le64_to_host (uint64_t v) [static] Converts the specified value if needed, knowing it is in little endian order.

Data structure

Parameters

	in	v	64-bit integer as read from a file
--	----	---	------------------------------------

Returns

integer converted to host's endianess

7.4.1.3.65. static force_inline uint32_t match_location (___Signature sig, uint32_-t goback) [static] Returns the offset of the match.

Engine query

Parameters

Returns

offset of match

7.4.1.3.66. static force_inline int32_t match_location_check (___Signature sig, uint32_t goback, const char * static_start, uint32_t static_len) [static] Like match_location(), but also checks that the match starts with the specified hex string.

Engine query

It is recommended to use this for safety and compatibility with 0.96.1

Parameters

	sig	- signature
	goback	- maximum length of signature (till start of last subsig)
	$static_start$	- static string that sig must begin with
Ī	$static_len$	- static string that sig must begin with - length

Returns

>=0 - offset of match -1 - no match

7.4.1.3.67. static force_inline uint32_t matches (___Signature sig) [static] Returns whether the specified subsignature has matched at least once.

Engine query

Parameters

```
sig | name of subsignature queried
```

Returns

1 if subsignature one or more times, 0 otherwise

7.4.1.3.68. static void* memchr (const void * s, int c, size_t n) [static] Scan the first n bytes of the buffer s, for the character c.

String operation

7.4. High level API

Parameters

in	s	buffer to scan
	c	character to look for
	n	size of buffer

Returns

a pointer to the first byte to match, or NULL if not found.

7.4.1.3.69. void* void int mem
cmp (const void * s1, const void * s2, uint
32_t n) Compares two memory buffers.

String operation

Parameters

in	s1	buffer one
in	<i>s</i> 2	buffer two
in	n	amount of bytes to copy

Returns

an integer less than, equal to, or greater than zero if the first n bytes of s1 are found, respectively, to be less than, to match, or be greater than the first n bytes of s2.

7.4.1.3.70. void* void memcpy (void *restrict dst, const void *restrict src, uintptr_t n) Copies data between two non-overlapping buffers.

String operation

Parameters

out	dst	destination buffer
in	src	source buffer
in	n	amount of bytes to copy

Returns

dst

7.4.1.3.71. void* memmove (void * dst, const void * src, uintptr_t n) Copies data between two possibly overlapping buffers.

String operation

Parameters

out	dst	destination buffer
in	src	source buffer
in	n	amount of bytes to copy

Returns

dst

7.4.1.3.72. void* memset (void * src, int c, uintptr_t n) Fills the specified buffer to the specified value.

String operation

Parameters

	out	src	pointer to buffer
	in	c	character to fill buffer with
ĺ	in	n	length of buffer

Returns

src

7.4.1.3.73. static force_inline int read PESectionName (unsigned char name[8], unsigned n) [static] Read name of requested PE section.

 \mathbf{PE}

Parameters

out	name	name of PE section
in	n	PE section requested

Returns

0 if successful, <0 otherwise

7.4.1.3.74. static force_inline bool readRVA (uint32_t rva, void * buf, size_t bufsize) [static] read the specified amount of bytes from the PE file, starting at the address specified by RVA.

 \mathbf{PE}

Parameters

	rva	the Relative Virtual Address you want to read from (will be converted to
		file offset)
out	buf	destination buffer
	bufsize	size of buffer

Returns

true on success (full read), false on any failure

7.4. High level API

CHAPTER 8

Copyright and License

8.1. The ClamAV Bytecode Compiler

The ClamAV Bytecode Compiler is released under the GNU General Public License version 2. The following directories are under the GNU General Public License version 2: ClamBC, docs, driver, editor, examples, ifacegen.

Copyright (C) 2009 Sourcefire, Inc.

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License version 2 as published by the Free Software Foundation.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.

It uses the LLVM compiler framework, contained in the following directories: llvm, clang. They have this copyright:

LLVM Release License

University of Illinois/NCSA Open Source License

Copyright (c) 2003-2009 University of Illinois at Urbana-Champaign. All rights reserved.

Developed by:

LLVM Team

University of Illinois at Urbana-Champaign

http://llvm.org

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal with

the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimers.
- * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimers in the documentation and/or other materials provided with the distribution.
- * Neither the names of the LLVM Team, University of Illinois at Urbana-Champaign, nor the names of its contributors may be used to endorse or promote products derived from this Software without specific prior written permission.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE CONTRIBUTORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS WITH THE SOFTWARE.

Copyrights and Licenses for Third Party Software Distributed with LLVM:

The LLVM software contains code written by third parties. Such software will have its own individual LICENSE.TXT file in the directory in which it appears. This file will describe the copyrights, license, and restrictions which apply to that code.

The disclaimer of warranty in the University of Illinois Open Source License applies to all code in the LLVM Distribution, and nothing in any of the other licenses gives permission to use the names of the LLVM Team or the University of Illinois to endorse or promote products derived from this Software.

The following pieces of software have additional or alternate copyrights, licenses, and/or restrictions:

 Program
 Directory

 ----- ------

 Autoconf
 llvm/autoconf

llvm/projects/ModuleMaker/autoconf
llvm/projects/sample/autoconf

CellSPU backend llvm/lib/Target/CellSPU/README.txt
Google Test llvm/utils/unittest/googletest

OpenBSD regex llvm/lib/Support/{reg*, COPYRIGHT.regex}

It also uses re2c, contained in driver/clamdriver/re2c. This code is public domain:

Originally written by Peter Bumbulis (peter@csg.uwaterloo.ca)

Currently maintained by:

- * Dan Nuffer <nuffer@users.sourceforge.net>
- * Marcus Boerger <helly@users.sourceforge.net>
- * Hartmut Kaiser <hkaiser@users.sourceforge.net>

The re2c distribution can be found at:

http://sourceforge.net/projects/re2c/

re2c is distributed with no warranty whatever. The code is certain to contain errors. Neither the author nor any contributor takes responsibility for any consequences of its use.

re2c is in the public domain. The data structures and algorithms used in re2c are all either taken from documents available to the general public or are inventions of the author. Programs generated by re2c may be distributed freely. re2c itself may be distributed freely, in source or binary, unchanged or modified. Distributors may charge whatever fees they can obtain for re2c.

If you do make use of re2c, or incorporate it into a larger project an acknowledgement somewhere (documentation, research report, etc.) would be appreciated.

8.2. Bytecode

The headers used when compiling bytecode have these license (clang/lib/Headers/{bcfeatures,bytecode*}.h):

Copyright (C) 2009 Sourcefire, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS "AN IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The other header files in clang/lib/Headers/ are from clang with this license (see individual files for copyright owner):

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY,

108 8.2. Bytecode

FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

When using the ClamAV bytecode compiler to compile your own bytecode programs, you can release it under the license of your choice, provided that you comply with the license of the above header files.

APPENDIX A

Predefined macros

```
77 #Jahrins PONTER WEFFE ohe

# define NTRE_TYPE short

78 #define NTRE_TYPE short

79 #define NTRE_TYPE long int

# define NTRE_TYPE long

# define DECLAMA_METHOD | 0

# define DECLAMA_TOTAL | 1

# define NTRE_TYPE long int

# define NTRE_TYPE long

# defin
```