Documentation MyCoRe – WCMS-Module

Authors: Andreas Trappe Michael Brendel

Toc:

Introduction	3
How does MyCoRe-WCMS work	4
Architecture	
WCMS-module in general	
How does User interface builds a web page	
XSL framework	
Templates	7
Installation	8
DocPortal	8
Configuration	10
How to change the default template	10
Manage access to WCMS with WCMSUserDB.xml	11
Introduction	11
User database of the WCMS	
Usage	

Introduction

Key functions:

- Add, Edit, Delete and translate web content
- Distributed Web-Browser bases administration
- Automatic generation of menu structures
- Templates
- Multi lingual
- Sitemap
- Logging, Backup
- "Plug and Play" installation

How does MyCoRe-WCMS work

Architecture

WCMS-module in general

User interface

- templates
- xml files (web pages)
- misc. Web content (images, JavaScript, etc.)
- XSL Stylesheets
- Navi structure base (navigation.xml)

Admin interface

- Servlets
- XSL Stylesheets
- Configuration
- (mycore.properties.wcms)
- Backup / Loggings
- Navigation base (navigation.xml)

Abbildung 1 - WCMS module

The WCMS-Module in general consists of two main parts: User interface and admin interface.

User interface is responsible for generation and providing of web pages. It uses XML-Navigation Base to create menus, and XML-files for displaying right Web-Pages and a couple of XSL-style sheets to build the framework of the Website (watch XSL framework).

Admin module is responsible for management of web pages displayed by the User interface.

It uses Servlets to read, write... web content and modifications on navigation base.

How does User interface builds a web page




Abbildung 2 - Building a web page by User module

XSL framework




Abbildung 3 - XSL framework



Installation

The installation consists of two main parts.

- 1. At first the non generic parts of the WCMS will be copied to the target application (e.g. DocPortal).
- 2. Afterwards the application specific adaptations have to be done. Thenceforward the installation will be automatically executed by running the mycoresample-application ant webapps.

DocPortal

To install MyCoRe-WCMS ensure the latest version of MyCoRe, Docportal, and MyCoReSample (www.mycore.de) is installed.

Copy module to application:

1. Plugin Module

Go to \$MYCORESAMPLE_HOME/ ant wcms

Configuration:

2. Point Default menu entries to your server

open \$MYCORESAMPLE_HOME/modules/modulewcms/uif/web/common/navigation.xml replace "path_to_mycore_server" by DNS-Name of your MyCoRe-Server E.g.: Your MyCoRe-Server is reachable at: "http://www.mycoreServer.de/mycore" à replace "path_to_mycore_server" by "http://www.mycoreServer.de/mycore"

open \$MYCORESAMPLE_HOME/modules/module-wcms/uif/web/index.html replace "path_to_mycore_server" by DNS-Name of your MyCoRe-Server

3. Adapt mycore.properties.wcms

open \$MYCORESAMPLE_HOME/modules/modulewcms/aif/config/mycore.properties.wcms replace dummy paths by real ABSOLUTE paths of your Mycore-Applications

Install

4. Install Module

cd \$MYCORESAMPLE_HOME ant webapps

5. Set file system permissions

WCMS-Servlets must have the following permissions (the locations you have set in mycore.properties.wcms):

- a) Read: "wcmsUserDBFile"
- b) read + write: "content section" RECURSIVELY
- c) read + write: "navigationFile"
- d) read + write: "backupPath" RECURSIVELY
- e) read + write: "logFile"

f) read + write: "footer"

g) read + write: "documentPath"h) read + write: "imagePath"

6. Restart Web-Application-Server

Usage

Call website and log into WCMS (WCMS button right above). The default username is admin with password wcms.

Try to add, edit a page and assign different templates and take a look at the effect to your website...

Configuration

How to change the default template

1. Reset entry in navigation base

- a) open \$navigationFile
- b) go to root tag <navigation ... />
- c) replace value of attribute template="template_nameOfDefaultTemplateRightNow" by template="template newNameOfDefaultTemplate"

2. Reset entry in chooseTemplate.xsl

- a) open \$MYCORESAMPLE_HOME/modules/module-wcms/uif/xsl/core/chooseTemplate.xsl
- b) replace in the area of "set name of default template" the following: <xsl:call-template name="template_nameOfDefaultTemplateRightNow"> by
- <xsl:call-template name="template_newNameOfDefaultTemplate">
- c) cd \$MYCORESAMPLE_HOME
- d) ant webapps

Manage access to WCMS with WCMSUserDB.xml

Introduction

The actual implementation of the WCMS doesn't allow to administrate any user data using a web oriented GUI. Thus, to add, delete or change users or user informations a system administrator has to configure the user database and possibly has to execute the userPassword encoder of the WCMS manually.

User database of the WCMS

The user database of the WCMS is a simple XML file called WCMSUserDB.xml. Each user got one entry in that database storing his usergroup he belongs to, his userID and userPassword and his real name. Furthermore a list of root nodes will be stored standing for elements of the navigation.xml under wich content can be changed.

There are 4 userClass definable:

- "systemAdmin" (do everything)
- "admin" (add, delete, edit, tranlate)
- "editor" (add, edit, translate)
- "author" (add, translate)

Location of the database

Normally the user database can be found at the following position:

\$DOCPORTAL HOME/modules/wcms/config/WCMSUserDB.xml

Structure of the database

As already mentioned, the user database is a simple xml file storing user informations as attributes of the user element. The root nodes, under wich the user can add and change content, will be stored as child elements of the user parent element.

```
Example 1: WCMSUserDB.xml

+------+

<?xml version="1.0" encoding="ISO-8859-1"?>

<userdb>

<user userClass="systemAdmin"
```

```
userID="sysAd"
    userPassword="ee7c6277441abd6d87367c3a7c5312ee"
    userRealName="Systemadministrator">
  <rootNode href="no">navi-main</rootNode>
  <rootNode href="no">navi-below</rootNode>
 </user>
 <user userClass="admin"
    userID="admin"
    userPassword="953320848fa1ed55c09031bc45bc9369"
    userRealName="Andreas Trappe">
   <rootNode href="no">navi-main</rootNode>
   <rootNode href="no">navi-below</rootNode>
 </user>
 <user userClass="editor"
    userID="micedit"
    userPassword="ebb5d7efc0472ac77534a55a7d1ffd"
    userRealName="Michael Brendel">
  <rootNode href="no">navi-main</rootNode>
  <rootNode href="no">navi-below</rootNode>
 </user>
 <user userClass="author"
    userID="author ilm"
    userPassword="5a671c66aefea124cc08b76ea6d30bb"
    userRealName="Torsten Schmidt">
  <rootNode href="yes">
   /content/main/information/ilmenau.xml
  </rootNode>
  <rootNode href="yes">
   /content/below/ilmenau/diss_ilmenau.xml
  </rootNode>
 </user>
 <user userClass="author"
    userID="transengl"
    userPassword="583ce7497cda5ca007553ce902e"
    userRealName="Jutta Klein">
  <rootNode href="no">navi-main</rootNode>
  <rootNode href="no">navi-below</rootNode>
 </user>
</userdb>
```

Adding a new user to the database

To add a new WCMS user to the database you have to edit the WCMSUserDB.xml file. At first the new user should be classified ito an userClass.

After the classification you have to select a userID and a userPassword for the new user or the user has already given you a userID and userPassword he likes to use. Either way you have to encrypt the userPassword manually. This can be done by using the HashCipher.class of the WCMS. The HashCipher.class should be called like this:

CLASSPATH_of_WCMS:>java wcms.util.HashCipher Password

where CLASSPATH_of_WCMS is the JAVA CLASSPATH the Web application is looking for classes. Normally this should be:

\$MYCORESAMPLE_HOME/webapp/WEB-INF/classes

<"String"> is the parameter wich will be encrypted. Copy and paste the output to the userPassword attribute of the new user. The last step to add a new user is to define his root nodes under wich he can add or modify content. A list of available root nodes can be found in the navigation.xml file. The navigation.xml file again can be found at the following position:

\$MYCORESAMPLE_HOME/modules/wcms/common/navigation.xml

Valid root nodes are either complete menus like navi-main or navi-below (wich are elements of navigation.xml and mark the corresponding menu) or only parts of a menu. In the case of root nodes being only parts of a menu respectivly an item element in the navigation.xml file, the href attribute has to be used instead of the element name and the rootNode attribute "href" in the WCMSUserDB.xml has to be set to "yes".

Usage