Lesson 3

### **Objectives**

• Describe how to run the core Flight System (cFS) from the GUI and from the command line


# Starting the cFS from the GUI (1 of 3)

Open a terminal window and issue the following commands (assumes you are starting in git clone location):

cd cfs-basecamp/qnd-sys/app . ./setvars.sh python3 basecamp.py

If you see the following error, then either setvars.sh wasn't run or the cFS has not been built and the python libraries don't exist.

grandpa-dave@ubuntu:~\$ cd cfs-basecamp/




Slide 3

# Starting the cFS from the GUI (2 of 3)

### Click <Start> to run the cFS in a new Linux process

After a several seconds messages will appear in the 'cFS Process Window' to indicate the cFS is running



## Starting the cFS from the GUI (3 of 3)

If you scroll up in the cFS Process Window you can find when cfe\_es\_startup.scr is opened

```
CFS Process Window Time: 1049773

1980-013-03:32:10.58743 CFE_ES_StartApplications: Opened ES App Startup file: /cf/cfe_es_startup.scr
1980-013-03:32:10.58762 CFE_ES_ParseFileEntry: Loading shared library: /cf/cfe_assert.so
1980-013-03:32:10.58801 [BEGIN] OFE FUNCTIONAL TEST
1980-013-03:32:10.58802 [BEGIN] O1 CFE_STARTUP
1980-013-03:32:10.58803 CFE_ES_ParseFileEntry: Loading shared library: /cf/osk_c_fw.so
OSK C Application Framework Library Initialized. Version 4.0.0
1980-013-03:32:10.64302 CFE_ES_ParseFileEntry: Loading file: /cf/osk_c_demo.so, APP: OSK_C_DEMO
1980-013-03:32:10.71270 CFE_ES_ParseFileEntry: Loading file: /cf/ci_lab.so, APP: CI_LAB_APP
1980-013-03:32:10.72164 CFE_ES_ParseFileEntry: Loading file: /cf/sch_lab.so: cannot open shared object file: No such file or directory
1980-013-03:32:10.72197 CFE_ES_ParseFileEntry: Loading file: /cf/sch_lab.so, APP: SCH_LAB_APP
1980-013-03:32:10.72201 CFE_ES_LoadModule: Could not load file:/cf/sch_lab.so. EC = -1
1980-013-03:32:10.72209 CFE_ES_ParseFileEntry: Loading file: /cf/ffile_mgr.so, APP: FILE_MGR
1980-013-03:32:10.72241 CFE_ES_ParseFileEntry: Loading file: /cf/file_kfer.so, APP: FILE_MGR
```

A successful startup includes success messages from each library and app as they are loaded and initialized

# **Starting the cFS from the Command Line** (1 of 2)

Open a terminal window and issue the following commands (assumes start in git clone location):


```
cd cfs-basecamp/cfe-eds-framework/build/exe/cpu1
./core-cpu1
```

```
grandpa-dave@ubuntu:~/cfs-basecamp$ cd cfe-eds-framework/build/exe/cpu1/
grandpa-dave@ubuntu:~/cfs-basecamp/cfe-eds-framework/build/exe/cpu1$ ./core-cpu1
OS_BSP_Initialize():Maximum user msg queue depth = 10
CFE PSP: Default Reset SubType = 1
CFE PSP: Default CPU ID = 1
CFE PSP: Default Spacecraft ID = 66
CFE PSP: Default CPU Name: cpu1
OS Posix GetSchedulerParams():189:Policy 1: available, min-max: 1-99
OS Posix GetSchedulerParams():189:Policy 2: available, min-max: 1-99
OS Posix TaskAPI Impl Init():375:Selected policy 2 for RT tasks, root task = 99
OS Posix TaskAPI Impl Init():392:Could not setschedparam in main thread: Operation not permitted (1)
CFE PSP: Instantiated software timebase 'cFS-Master' running at 10000 usec
CFE PSP: Using POSIX monotonic clock as CFE timebase
CFE PSP: Using MMAP simulated EEPROM implementation
CFE PSP: Physical RAM access not implemented
CFE PSP: I/O Port access not implemented
CFE PSP: EEPROM Range (2) created: Start Address = 7F1CE43B7000, Size = 00080000 Status = 0
CFE PSP: Starting the cFE with a POWER ON reset.
CFE_PSP: Clearing out CFE CDS Shared memory segment.
CFE PSP: Clearing out CFE Reset Shared memory segment.
CFE PSP: Clearing out CFE User Reserved Shared memory segment.
1980-004-06:22:10.24802 CFE_ES_SetupResetVariables: POWER ON RESET due to Power Cycle (Power Cycle).
1980-004-06:22:10.24806 CFE ES Main: CFE ES Main in EARLY INIT state
```

# Starting the cFS from the Command Line (2 of 2)


#### The GUI can still be used with a cFS process that was not started using the GUI, however

- 1. The *Image* name will not be loaded
- 2. The *cFS Process Window* will be blank. The terminal window where the cFS was started serves as the cFS Monitor Display
- 3. Flight events will still appear in the Ground & Flight Events window



## **Verify Operations**


Using the Quick Cmd 'cFE Version' option is a quick way to verify the cFS target is operational



'cFE Version' sends a cFE Executive Service No Op command that reports the current cFE version in an event message

```
EVS Port1 66/1/CFE_ES 92: Build 202209011309 by grandpa-dave@ubuntu, config basecamp EVS Port1 66/1/CFE_ES 3: No-op command: cFS Versions: cfe v6.8.0-rc1+dev1024, osal v5.1.0-rc1+dev619, psp v1.5.0-rc1+dev124
```

The No Op command also increments ES's command counter that is reported in its Housekeeping telemetry



## **Potential Startup Error**

#### A known potential startup error is a permission denied as shown here

```
cFS Process Window Time: Null
exe_dir = /home/grandpa-dave/test/cfs-basecamp/cfe-eds-framework/build/exe/cpu1
exe_file = core-cpu1
OS_Posix_GetSchedulerParams():189:Policy 1: available, min-max: 1-99
OS_Posix_GetSchedulerParams():189:Policy 2: available, min-max: 1-99
OS_Posix_TaskAPI_Impl_Init():375:Selected policy 2 for RT tasks, root task = 99
OS_Posix_TaskAPI_Impl_Init():392:Could not setschedparam in main thread: Operation not permitted (1)
OS_API_Init():151:OS_API_Impl_Init(0x1) failed to initialize: -1
OS_API_Init():228:Warning: Microsecs per sec value of 0 does not equal 1000000 (MicroSecPerTick: 0 TicksPerSecond: 0)
OS_printf():300:BUG: OS_printf() called when OSAL not initialized: CFE_PSP_Panic Called with error code = 0x%08X. Exiting.
OS_printf():300:BUG: OS_printf() called when OSAL not initialized: The cFE could not start.
```

#### Potential causes and solutions


- The OSAL has a permissive mode setting
- If you perform a 'make SIMULATION=native prep' permissive mode should be set, and you shouldn't get
  this error
- Before you rerun 'make prep', you should run 'make distclean' to clear all cmake caches
- If you continue to get the error, you can run in privileged mode
  - From the GUI you must set the following basecamp.ini parameters and restart the GUI:
     SUDO\_START\_CFS = True, PASSWORD = your account password (no quotes)
  - From the command line run 'sudo ./core-cpu1'

Slide 8

## Stopping the cFS from the GUI

### From the GUI click <Stop> to terminate the cFS process

- 1. The cFS Process terminates
- 2. Time changes to *Null*
- 3. Image changes to None Selected



If the cFS is started from a terminal window, the GUI <Stop> button will have no effect

Slide 9

## **Stopping the cFS from the Command Line**

#### Enter Ctrl-c in the terminal window that was used to start the cFS


1. The exception is caught and cFS process is terminated

```
1980-012-14:03:34.44183 CFE_ES_Main: CFE_ES_Main entering APPS_INIT state
1980-012-14:03:34.44184 CFE_ES_Main: CFE_ES_Main entering OPERATIONAL state
EVS Port1 66/1/CFE_TIME 21: Stop FLYWHEEL
EVS Port1 66/1/KIT_SCH 404: Major Frame Sync too noisy (Slot 1). Disabling synchronization.
^C1980-012-14:03:45.46238 CFE_ES_RunExceptionScan: ExceptionID 0x1110001 in TaskID 0: Caught SIGINT 1980-012-14:03:45.46240 CFE_ES_RunExceptionScan: Processor Reset count not reached (1/2)
CFE_PSP: Exiting cFE with PROCESSOR Reset status.

CFE_PSP: Shutdown initiated - Exiting cFE
CI delete callback -- Closing CI Network socket.
```

### Terminate a cFS process from a terminal window not used to start the cFS

- 1. Determine the cFS process identifier
- 2. Use elevated privileges to "kill" the process



#### **cFS Target Monitor Terminal**

```
EVS Port1 66/1/CFE_TIME 20: Start FLYWHEEL
EVS Port1 66/1/CFE_TIME 21: Stop FLYWHEEL
1980-012-14:04:59.78396 CFE_ES_RunExceptionScan: ExceptionID 0x1110002 in TaskID 0: Caught Signal 15
1980-012-14:04:59.78397 CFE_ES_RunExceptionScan: Maximum Processor Reset count reached (2)
CFE_PSP: Exiting cFE with POWERON Reset status.
CFE_PSP: Critical Data Store Shared memory segment removed
Reset Area Shared memory segment removed
User Reserved Area Shared memory segment removed

CFE_PSP: Shutdown initiated - Exiting cFE
CI delete callback -- Closing CI Network socket.
```

Slide 10