
Skip to content Workflow & Examples

Simple Drivers can be configured from the pop-over that appears when adding a new Driver. When adding multiple Drivers or for more advanced configurations, it is useful to have open the Drivers Editor.


Transform Driver

Control a property with an object's transform. In this example, the Y rotation of Object 2 will be driven by the X position of Object 1. Starting from a simple setup with two objects:

1. Add a Driver to the *Rotation Y* property of the second object via the context menu or with Ctrl - D.




- 2. Open the *Drivers Editor* and select the *Y Euler Rotation* property in the channels region.
- 3. Open the Sidebar region and select the *Drivers* tab.
- 4. Configure the driver to be the Averaged Value of a Transform Channel of the first object.



5. Experiment with moving the first object and notice how it affects the Y rotation of the second object.

Delipiou Lapioudion Oldion i dini

Orbit an object's position around a point with a custom *Scripted Expression*. The object's position will change when scrubbing the timeline. Using trigonometry, circular motion can be defined in 2D using the sine and cosine functions. (See Unit Circle.) In this example, the current frame is used as the variable that induces the motion. frame is a Simple Expression that corresponds to <code>bpy.context.scene.frame_current</code>.



- 1. Add a driver to the X Location property.
 - 1. Set the *Driver Type* to *Scripted Expression*.
 - 2. Add the expression 0 + (sin(frame / 8) * 4), where:
 - frame/8: is the current frame of the animation, divided by 8 to slow the orbit down.
 - (sin()*4): multiplies the result of sin(frame/8) by 4 for a bigger circle.
 - 0 + : is used to control the offset to the orbit center point.
- 2. Add a driver to the Y Location property with the expression $0 + (\cos(frame / 8) * 4)$.
- 3. Scrub the timeline to see the effect. Experiment with the variables to control the size and center of the orbit.

Custom Function - Square Value

Create a custom function to get the square of a value (i.e. $value^2$). Adding the function to the *Driver Namespace* allows it to be used from driver expressions. The *Driver Namespace* has a list of built-in functions for use in driver expressions, as well as constants such as π and e. These can be inspected via the Python Console:

To add a new function to the *Driver Namespace*, the function itself needs to be implemented and then added to the bpy.app.driver_namespace.

1. Add the following to the Text Editor inside Blender and press Run Script.

```
import bpy
def square(val):
```

```
"""Returns the square of the given value"""
return val * val

# Add function to driver_namespace.
bpy.app.driver_namespace['square'] = square
```

- 2. Add a driver with a Scripted Expression such as square (frame).
- 3. Observe the effect when scrubbing the timeline.

There are more custom function examples available in Blender's Text Editor Templates • Python • Driver Functions. Since Simple Expressions cannot access custom functions, using them only makes sense for complex computations.

Warning

Trying to replace built-in entries of the driver namespace may result in undefined behavior.

View Layer Attribute Lookup

The material Attribute Node in the View Layer mode automatically searches for the attribute property in multiple locations. This, for example, can allow setting a certain value of the custom attribute at the Scene or World level, and then overriding it differently for one View Layer.

Context Properties of drivers don't implement this behavior, so if necessary it has to be manually emulated via fallback values and a conditional expression (conditions are Simple Expressions).

For an attribute named attr, the node tries the following six RNA path lookups in order:

- ["attr"] in the active View Layer (custom property).
- attr in the active View Layer (built-in property).
- ["attr"] in the active Scene.
- attr in the active Scene.
- world["attr"] in the active Scene.
- world.attr in the active Scene.


Depending on the specific property it may be sufficient to check only a subset of these locations. For example, the image on the right shows how to access an attribute that is known to definitely be a custom property with a color value.


Driver variables accessing locations that are not final in the lookup chain should use fallback values that are invalid for the attribute (e.g. negative color values), which can then be checked by the conditional expression. The final variable should fallback to a valid default value to be used when the property is not set at all.

Shape Key Drivers

Improved Mesh Deformation

Fix intersection problems that happen when using armatures and weight painting, especially at joints. Shape keys can also be used to tweak and refine a rig, for example to suggest muscle formations. In this example, a shape key is used to improve the deformation at the elbow of a rudimentary arm.





Left: Skeletal mesh deformation without correction. Right: Corrective shape key applied

Setup

- 1. Add a mesh (in this example, a cylinder with loop cuts).
- 2. Add an armature with a chain of bones.
- 3. Skin the mesh to the armature using weight painting.

(Note: to parent the mesh to the armature: select the mesh first, then the armature and use Ctrl - P to parent with auto weights.)

Experiment with posing the armature and observe the deformation at the joint. To fix intersection problems or angles that look unsatisfactory, you can associate a Shape Key with a pose.

Shape Key

- 1. Pose the armature such that the problems are visible. Be sure to cover the extreme poses that you want to support for the rig.
- 2. With the mesh selected, add a new Shape Key in addition to the Basis key. Properties Mesh tab Shape Keys
- 3. In order to author the shape key on top of the armature deformation, enable both *Edit Mode Display* and *Cage Editing* in the Armature modifier. Properties Modifiers tab Armature Modifier Header
- 4. Enter Edit Mode and select the new shape key in the properties panel. Adjust the vertices as desired. Select the *Basis* key to toggle between to original mesh and your edits. (Note: be careful to apply edits only to your shape and not to the original mesh or other existing keys.)

Once you are satisfied with how the deformation looks for the problematic pose, you'll need to configure a driver to activate the shape smoothly when entering that position.

Driver


- 1. Add a driver to the *Value* of the shape key you've created.
- 2. Open the Drivers Editor and select the driver.

Method 1 – Direct mapping to a bone rotation value

A simple way to configure the driver is with a direct correspondence of the value of a bone's rotation channel to the shape key activation *Value*. This method has the disadvantage of relying on a single channel of a bone's rotation which might be insufficient to precisely express the condition under which the shape key should be activated.

In the Drivers tab, select the Averaged Value of the rotation of the bone you are posing.
 Understand the rotation axis that you are interested in by enabling axes display in the armature or by observing the bone's transform value in the Properties.

Select the rotation channel and set it to local, meaning, the bone's rotation value relative to its parent bone.






- 2. Manually set points in the driver curve by selecting a handle and dragging it or inserting values in the *F-Curve* tab. The Y axis represents the shape key *Value*, which should go from 0.0 to 1.0. The X axis is usually the frame, but for this driver it represents the rotation value radians. You can have more than two points in the curve and tweak the transitions with the handles in the curve view (^G to move).
- 3. To verify that the driver behaves correctly, deselect the option to only show drivers for selected objects. This way, you can pose the armature and keep an eye on the driver.

Method 2 – Rotational difference to a target bone

This method requires an additional *target* or *corrective* bone, but it better expresses the spatial condition in 3D space of the bone that is causing the problem

- 1. In armature Edit Mode, add a new bone extruded from Bone 1, in the position at which Bone 2 should have the shape key active. This type of bones usually follow a naming convention such as "TAR-" (target) or "COR-" (corrective).
- 2. In the Drivers tab, select the *Averaged Value* of the rotational difference between the bone you are rotating and the target bone. A rotational difference is the minimum angle between two objects in World Space. It is therefore important that the bones have the same root, so that the only thing affecting the angle between the bones is the rotation of one of them. When the deformation bone (Bone 2) reaches the target rotation (TAR-Bone 2) the rotational difference will be 0°.




- 3. Manually adjust the driver curve handles so that the shape key *Value* (Y axis) is 1.0 when the rotational difference (X axis) is 0°. The *Value* should be 0.0 when the arm is extended, at which point the rotational difference should be around 90° or more (in radians).
- 4. See the steps in Method 1 on how to adjust the curve handles and confirm that the functionality is working. Pose the armature to verify that the ranges are correct.

Chained Relative Shape Keys


Activate different shape keys in succession. In this example, moving a single bone will activate first *Key 1* and then *Key 2*. See also relative shape keys n additively.

Shape Keys

Add two shape keys to a mesh, besides the Basis.



Add an armature with a single bone to control the shape keys. The goal is to activate the keys in succession as this bone moves up.




As shown in the picture above, when the bone is halfway up, both *Key 1* and *Key 2* have an influence. It is a matter of preference if *Key 1* should be at its maximum *Value* before *Key 2* starts to become active, or how much they should overlap. This example shows a seamless blend.

For a seamless blend where there is overlap, *Key 1* should have a *Value* of 0.0 when the bone is at the bottom and increase linearly to 1.0 until th bone is past the midpoint height. *Key 2* should have a value of 0.0 before the midpoint height and then increase at the same rate than *Key 1* until reaching *Value* 1.0 when the bone is at maximum height.

- 1. Add a driver to the *Value* of *Key 1* and *Key 2*. In the *Drivers* tab, configure both drivers to be the *Averaged Value* of a variable with the bone's Z location.
- 2. Determine the range of the bone's motion in the World Z axis by moving it up so that it is aligned with the top of the mesh when both keys are active. Here we will use [0.0, 2.5].
- 3. Configure the driver functions so that the *Value* of the shape keys (Y axis) is as desired for the bone's height (X axis). The driver functions should be linear, therefore, they can be defined analytically with a function of type (y = a + bx), where (a) is an offset in (y) and (b) is the slope.
 - 1. In the Modifiers tab, add a Generator of type Extended Polynomial for both drivers.
 - 2. Play with the values of $\langle a \rangle$ and $\langle b \rangle$ so that the curves go from [0.0, 1.0] in the Y axis and from [0.0, 2.5] in the X axis. The curves should overlap in the mid area of the X axis and they should have the same slope ($\langle b \rangle$).

Possible values are Key 1: (y = 0.0 + 0.6x) and Key 2: (y = -0.5 + 0.6x).



Note that the functions go outside the range [0.0, 1.0] for the shape keys' *Value*, but that has no effect because *Value* is clamped in a *Ranş* in the *Shape Keys* panel.

view iransiauon Report issue on this page