


#### FFX CACAO - API

JAY FRASER



```
#ifndef FFX_CACAO_ENABLE_PROFILING
#define FFX_CACAO_ENABLE_PROFILING 0
#endif

#ifndef FFX_CACAO_ENABLE_D3D12
#define FFX_CACAO_ENABLE_D3D12 1
#endif
```

### FFX\_CACAO

 First in the ffx\_cacao.h header disable/enable desired features by defining the FFX\_CACAO\_ENABLE\_\* macros as 0 or 1 respectively.



### FFX\_CACAO INITIALISATION

To initialise FFX CACAO, the input and output buffers must be passed to FFX CACAO. The buffers required are as follows:

- A depth buffer with inverse depths from the scene as calculated by the projection matrix.
- An optional normal buffer for the scene.
- A single channel output buffer.

All input and output buffers must be the same size.



```
#include "ffx cacao.h"
size t contextSize = ffxCacaoD3D12GetContextSize();
FfxCacaoD3D12Context *context = (FfxCacaoD3D12Context*)malloc(contextSize);
ID3D12Device *device = ...;
FfxCacaoStatus status = ffxCacaoD3D12InitContext(context, device);
if (status != FFX_CACAO_STATUS_OK) {
        // handle errors...
FfxCacaoD3D12ScreenSizeInfo ssi = {};
ssi.width = ...;
ssi.height = ...;
ssi.depthBufferResource = ...; // ID3D12Resource* for the depth buffer
ssi.depthBufferSrvDesc = ...;
ssi.normalBufferResource = ...; // Optional ID3D12Resource* for the normal buffer
ssi.normalBufferSrvDesc = ...;
ssi.outputResource = ...; // ID3D12Resource* for the output buffer
ssi.outputUavDesc = ...;
FfxCacaoBool downsampleSsao = ...;
status = ffxCacaoD3D12InitScreenSizeDependentResources(context, &ssi, downsampleSsao);
if (status != FFX CACAO STATUS OK) {
        // handle errors...
```

### FFX\_CACAO INITIALISATION

- Allocate a CACAO context by getting its size with ffxCacaoD3D12GetContextSize
- Initialise the context with ffxCacaoD3D12InitContext and passing an ID3D12Device\*.
- Fill in an FfxCacaoD3D12ScreenSizeInfo struct
- Initialise screen size dependent resources with ffxCacaoD3D12InitScreenSizeD ependentResources



```
// Delete current screen size dependent resources
status = ffxCacaoD3D12DestroyScreenSizeDependentResources(context);
if (status != FFX_CACAO_STATUS_OK) {
       // handle errors...
// Recreate screen size dependent resources
FfxCacaoD3D12ScreenSizeInfo ssi = {};
ssi.width = ...;
ssi.height = ...;
ssi.depthBufferResource = ...;
ssi.depthBufferSrvDesc = ...;
ssi.normalBufferResource = ...;
ssi.normalBufferSrvDesc = ...;
ssi.outputResource = ...;
ssi.outputUavDesc = ...;
FfxCacaoBool downsampleSsao = ...;
status = ffxCacaoD3D12InitScreenSizeDependentResources(context, &ssi, downsampleSsao);
if (status != FFX CACAO STATUS OK) {
       // handle errors...
```

# FFX\_CACAO SCREEN SIZE CHANGE

changes, first free screen size dependent resources with ffxCacaoD3D12DestroyScreenSizeDependentResources then recreate resources with ffxCacaoD3D12InitScreenSizeDependentResources



```
FfxCacaoSettings settings = {};
settings.radius = ...; // world space radius of occlusion sphere
settings.shadowMultiplier = ...; // effect strength multiplier
settings.shadowPower = ...; // effect strength power modifier
settings.shadowClamp = ...; // effect strength max limit (applied after multiplier)
settings.horizonAngleThreshold = ...; // minimum angle between surface normal and occlude
settings.fadeOutFrom = ...; // world space distance to start fading out the effect
settings.fadeOutTo = ...; // world space distance to finish fading out the effect
settings.qualityLevel = ...; // effect quality, affects number of taps etc
settings.adaptiveQualityLimit = ...; //
settings.blurPassCount = ...; // number of edge sensitive blurs to apply
settings.sharpness = ...; // how much to bleed over edges
settings.temporalSupersamplingAngleOffset = \dots; // a sampling angle offset which may be
updated per frame to help with temporal supersampling
settings.temporalSupersamplingRadiusOffset = \dots; // a sampling radius offset which may be
updated per frame to help with temporal supersampling
settings.detailShadowStrength = ...; // adds detail using neighbouring pixel depths
settings.generateNormals = ...; // set this option to true to generate a normal buffer from
the depth buffer, or false if a normal buffer is provided
settings.bilateralSigmaSquared = ...; // Gaussian blur parameter for bilateral upsampler.
Smaller values correspond to less blur
settings.bilateralSimilarityDistanceSigma = ...; // similarity parameter for bilateral
upsampler. Smaller values make the blur bleed less over edges
status = ffxCacaoD3D12UpdateSettings(context, &settings);
if (status != FFX CACAO STATUS OK) {
        // handle errors
```

# FFX\_CACAO UPDATE SETTINGS

- Settings can be set/updated by filling in an FfxCacaoSettings struct and calling ffxCacaoD3D12UpdateSettings
- Settings changed by using this function may safely be changed per frame



### FFX\_CACAO DRAW

The draw call for FFX CACAO requires two matrices as input:

- The matrix "proj", which is the projection matrix used for rendering the scene.
- The matrix "normalsToView", which is used to transform the normals in the normal buffer to viewspace



### FFX\_CACAO DRAW

- Allocate a CACAO context by getting its size with ffxCacaoD3D12GetContextSize
- Initialise the context with ffxCacaoD3D12InitContext and passing an ID3D12Device\*.
- Fill in an FfxCacaoD3D12ScreenSizeInfo struct
- Initialise screen size dependent resources with ffxCacaoD3D12InitScreenSizeD ependentResources



## FFX\_CACAO GETTING TIMINGS

Detailed timings for CACAO can be retrieved with the ffxCacaoD3D12GetDetailedTimin gs function. This returns an array of timings for different stages of CACAO from the previous frame. The timing in entry 0 is guaranteed to be the total time in GPU ticks that CACAO took in the previous frame.



#### FFX\_CACAO FINALISATION

 To correctly finalise CACAO, you must first destroy screen size dependent resources, and then destroy the CACAO context.

