Tectonic: An Academic Cyber Range

Cheatsheet

Tectonic is a cyber range designed to provide realistic cybersecurity scenarios for education and training through the deployment of networks, systems and applications that can be used to train users on cybersecurity topics. Key functionalities include customizable network configurations, real-time monitoring and automated attack simulations.

Scenario Management

Scenarios are defined using a scenario description yml file (usually description.yml inside the scenario directory) plus a lab edition file (usually <lab_name>.yml.

• Create base images:

```
tectonic -c ~/tectonic.ini <lab_edition_file> create-images
```

• Deploy scenario:

```
tectonic -c ~/tectonic.ini <lab_edition_file> deploy
```

• Destroy scenario [and base images]:

```
tectonic -c ~/tectonic.ini <lab_edition_file> destroy [--images]
```

• Show cyber range information (access IP addresses, credentials):

```
tectonic -c ~/tectonic.ini <lab_edition_file> info
```

Operations on machines

Operations done on machines in the scenario, after it is deployed.

• Get a console on a *single* machine:

```
tectonic -c ~/tectonic.ini <lab_edition_file> console <machine_spec>
```

• Reboot, shutdown or start machines in the scenario:

```
tectonic -c ~/tectonic.ini <lab_edition_file> [reboot|shutdown|start] <machine_spec>
```

• Recreate machines (go back to the initial state):

```
tectonic -c ~/tectonic.ini <lab_edition_file> recreate <machine_spec>
```

• Run an arbitrary ansible playbook:

```
tectonic -c ~/tectonic.ini <lab_edition_file> run-ansible -p <playbook> <machine_spec>
```

Machine specification The above commands expect machine specification options, which can be a combination of: guest (base) name (-g), instance number (-i), and copy number (-c).

For example, to reboot all copies of the machine victim of instances 3 and 4, one can run:

tectonic -c ~/tectonic.ini <lab_edition_file> [reboot|shutdown|start] -g victim -i 3,4 Instance and copy numbers can be specified either as a list: 1,2,3, as a range: 5-10, or as a combination: 2,4-6,8.

Connectivity to the scenario

• Teacher access:

Use tectonic console, or connect through ssh:

```
ssh -J ubuntu@<teacher_access_ip> <machine_ip>
```

teacher_access_ip is shown after scenario deployment and in the output of tectonic info.

• Student access:

```
ssh -J traineeXX@<student_access_ip> <entry_point_ip>
```

student_access_ip is shown after scenario deployment and in the output of the tectonic info command.

By default student usernames are of the form traineeXX, where XX is the instance number. Credentials can be either SSH public keys, generated passwords or both.

Only machines declared as entry points are accessible to the students.

• Copy files to/from machines:

Use the -J option to scp in the same way as above.

```
scp -J traineeXX@<student_access_ip> <source> <dest>
```

Port forwarding It is possible to forward ports to access services withing the scenario. To do that, use the -L option to ssh:

```
ssh -L localhost:<local-port>:<remote-ip>:<remote-port> <ssh-connection-options>
```

where **<ssh-connection-options>** connects to the scenario either as student or teacher, as above.

For example, to forward local port 80443 to port 443 on machine 10.0.1.5, use:

```
ssh -L localhost:80443:10.0.1.5:443 <ssh-connection-options>
```

You can then connect to localhost:80443 to access port 443 on machine 10.0.1.5.

File edition

For editing files within a scenario, you can use a console based text editor or run locally a text editor that supports remote connections, such as VSCode. Using the above ssh connection commands, VSCode can edit remote files, open a console and configure port forwardings. See https://code.visualstudio.com/docs/remote/ssh for more details.