## OCAAT

(Open Cluster Automated Analysis Tool)

Manual v1.0.0 (July 22, 2014)

## 1 Introduction

This is the manual of operation for the OCAAT code.

## 2 Synthetic clusters

## 2.1 IMF sampling

The initial mass function (IMF) is the distribution of initial masses for a population of stars. For a population of N stars with masses  $m_i$  and a total mass of  $M_T$ :

$$IMF \to \xi(m) = \frac{dn}{dm} \to dn = \xi(m)dm$$

$$M_T = \sum_{i=1}^{N} m_i \to M_T = C \int_{m_l}^{m_h} m(n)dn =$$

$$= C \int_{m_l}^{m_h} m\xi(m)dm$$

where  $m_l$  and  $m_h$  are the mass limits for the IMF ( $m_h$  is fixed to  $100 M_{\odot}$  in the code) and C is a normalization constant. Setting the total mass to unity,  $M_T = 1 M_{\odot}$ , allows us to obtain the normalization constant  $C_1$  and treat the normalized IMF as a PDF:

$$M_T = 1 M_{\odot} \rightarrow C_1 = \frac{1}{\int_{m_l}^{m_h} m\xi(m)dm}$$

and thus the normalized IMF can be written as:

$$PDF(m) = \xi(m)_{norm} = C_1 \xi(m)$$

This is the first step, performed by the get-IMF-PDF function for a given selected IMF (Chabrier 2001, Kro"upa et al. 1993, Kroupa 2002)

Once the PDF is generated, every time a new synthetic cluster is created the get-mass-dist function is called from within synth-cluster. This former function takes the PDF and samples a number of masses randomly from it, following the probabilities distribution given by the PDF, until the mass fixed by the total-mass parameter is achieved.

The get-mass-dist function thus returns a distribution of masses probabilistically sampled from a certain IMF, whose masses sum up to a total cluster mass.