## **GnuCOBOL** Manual

for GnuCOBOL 2.0

## Keisuke Nishida, Roger While, Brian Tiffin, Simon Sobisch

Edition 2.1 Updated for GnuCOBOL 2.0 22 December 2015

GnuCOBOL is a free and open-source COBOL compiler, which translates COBOL programs to C code and compiles it using GCC or other native operating system C compiler.

This manual corresponds to GnuCOBOL 2.0.

Copyright © 2002-2012, 2014-2015 Free Software Foundation, Inc. Written by Keisuke Nishida, Roger While, Brian Tiffin, Simon Sobisch. Permission is granted to make and distribute verbatim copies of this manual provided the copyright notice and this permission notice are preserved on all copies. Permission is granted to copy and distribute modified versions of this manual under the conditions for verbatim copying, provided that the entire resulting derived work is distributed under the terms of a permission notice identical to this one. Permission is granted to copy and distribute translations of this manual into another language,

under the above conditions for modified versions, except that this permission notice may be

stated in a translation approved by the Free Software Foundation.

# Table of Contents

1	Getting Started	1
	1.1 Hello World!	
<b>2</b>	Compile	2
	2.1 Compiler Options	2
	2.1.1 Help Options	
	2.1.2 Built Target	2
	2.1.3 Source Format	. 3
	2.1.4 Warning Options	4
	2.1.5 Configuration Options	4
	2.1.6 Debug Switches	
	2.1.7 Miscellaneous	
	2.2 Multiple Sources	
	2.2.1 Static Linking	
	2.2.2 Dynamic Linking	
	2.2.3 Building Library	
	2.2.4 Using Library	
	2.3 C Interface	
	2.3.1 Writing Main Program in C	
	2.3.2 Static linking with COBOL programs	
	2.3.3 Dynamic linking with COBOL programs	
	2.3.5 Dynamic linking with C programs	
	2.3.3 Dynamic mixing with C programs	11
3	Customize	12
_	3.1 Customizing Compiler	
	3.2 Customizing Library	
	0.2 Customizing Library	14
4	Optimize	13
_	4.1 Optimize Options	
	4.1 Optimize Options 4.2 Optimize Call	
	4.3 Optimize Binary	
	4.9 Optimize Binary	10
5	Debug	14
	5.1 Debug Options	14
6	Extensions not ISO/ANSI standard	15
U	•	
	6.1 SELECT ASSIGN TO	
	6.2 Indexed file packages	
	6.3 Extended ACCEPT statement	
	6.3.2 PROTECTED	
	6.3.3 SIZE	
	6.4 ACCEPT special keys.	
	6.4.1 Arrow keys	
	6.4.2 Backspace key	
	ı v	

6.4.3 6.4.4 6.4.5 6.4.6 6.4.7 6.5 Exte 6.5.1 6.5.2 6.5.3 6.5.4	Delete keys End keys Home keys Insert key Tab keys ended DISPLAY statement BELL BLANK ERASE SIZE	
-	em routines L_OC_GETOPT	
Appendi	$\mathbf{ix} \; \mathbf{A}$ cobchelp	21
Appendi	$\mathbf{i}\mathbf{x}\;\mathbf{B}$ cobclist-reserved	24
Appendi	ix C cobclist-intrinsics	36
Appendi	ix D cobclist-system	39
Appendi	$\mathbf{i}\mathbf{x}\;\mathbf{E}$ cobclist-mnemonics	41
Appendi	ix F Compiler Configuration	44
Appendi	$\mathbf{i}\mathbf{x}\;\mathbf{G}$ cobcrunhelp	47
H.1 Gen H.2 Gen H.3 Call H.4 File	ix H Runtime configuration  neral instructions  neral environment  ll environment  e I/O  eeen I/O	
$\mathbf{Index}\dots$		

## 1 Getting Started

### 1.1 Hello World!

This is a sample program that displays "Hello World":

```
--- hello.cob -----

* Sample COBOL program

IDENTIFICATION DIVISION.

PROGRAM-ID. hello.

PROCEDURE DIVISION.

DISPLAY "Hello World!".

STOP RUN.
```

The compiler is cobc, which is executed as follows:

```
$ cobc -x hello.cob
$ ./hello
Hello World!
```

The executable file name (i.e., hello in this case) is determined by removing the extension from the source file name.

You can specify the executable file name by specifying the compiler option -o as follows:

```
$ cobc -x -o hello-world hello.cob
$ ./hello-world
Hello World!
```

Using more modern sources.

```
---- hellonew.cob ------

*> Sample GnuCOBOL program
identification division.
program-id. hellonew.
procedure division.
display
   "Hello New World!"
end-display
goback.
------
$ cobc -x -free hellonew.cob
$ ./hellonew
Hello New World!
```

Showing the use of free format, to end of line comments, the goback verb, and proper use of terminator with end-display.

## 2 Compile

This chapter describes how to compile COBOL programs using GnuCOBOL.

## 2.1 Compiler Options

The compiler cobc accepts the options described in this section.

General syntax -

cobc [options] file [file ..]

A complete list of options can be displayed by using the help option.

## 2.1.1 Help Options

The following switches can be used for informational displays:

--help Display help screen (see Appendix A [cobc -help], page 21), -h will also display the help.

No further actions will be taken.

#### --version

Display compiler version, author package date and executable build date. -V will also display version.

No further actions will be taken.

--info Display build information along with default and current compiler configuration.

No further actions will be taken except for further display options.

-v Verbosely displays the programs invoked during compilations.

### --list-reserved

Display reserved words (see Appendix B [cobc –list-reserved], page 24). A Y/N field shows if the word is supported.<sup>1</sup> No further actions will be taken except for further display options.

#### --list-intrinsics

Display intrinsic functions (see Appendix C [cobc –list-intrinsics], page 36). A Y/N field shows if the function is implemented. No further actions will be taken except for further display options.

#### --list-system

Display system routines (see Appendix D [cobc –list-system], page 39). No further actions will be taken except for further display options.

### --list-mnemonics

Display mnemonic names (see Appendix E [cobc –list-mnemonics], page 41). No further actions will be taken except for further display options.

### 2.1.2 Built Target

The cobc compiler can handle \*.cob, \*.cbl as COBOL source code, \*.c for C source code, \*.o for object code, \*.i for preprocessed code and \*.so for dynamic modules and will do the right thing in terms of generation, compilation, or link.

The special input name - takes input from stdin which is assumed to be COBOL source, and uses a default output name of a.out (or a.so,c,o,i) as appropriate for the build type.

The following options specify the target type produced by the compiler:

<sup>&</sup>lt;sup>1</sup> Support may be partial or complete

- -E Preprocess only. Compiler directives are executed. Comment lines are removed. COPY statements are expanded.
  - The output is saved in file \*.i.
- -C Translation only. COBOL source files are translated into C files. The output is saved in file \*.c.
- -S Compile only. Translated C files are compiled by the C compiler to assembler code. The output is saved in file \*.s.
- -c Compile and assemble. This is equivalent to cc -c. The output is saved in file \*.o.
- -m Compile, assemble, and build a dynamically loadable module (i.e., a shared library).

  The output is saved in file \*.so.

  This is the default behaviour if not other options are given.<sup>2</sup>.
- -b Compile, assemble, and combine all input files into a single dynamically loadable module. Unless -o is also used, the output is saved using the first filename as \*.so.
- Include the main function in the output, creating an executable image. The main entry point being the outermost PROGRAM-ID.
   This option takes effect at the translation stage. If you give this option with -C, you will see the main function at the end of the generated C file.
- -j Run job after compilation. Either from executable with -x, or with cobcrun when compiling a module.
- -I <directory>

Add <directory> to copy/include search path

-L <directory>

Add <directory> to library search path

- -1 Link the library >
- -D <define>

Pass <define> to the COBOL compiler

-o <file> Place the output into <file>

Without any options above, the compiler builds a dynamically loadable module.

### 2.1.3 Source Format

GnuCOBOL supports both fixed and free source format.

The default format is the fixed format. This can be explicitly overwritten by one of the following options:

- -free Free format. The program-text area starts in column 1 and continues till the end of line. Effectively 255 characters in GnuCOBOL. -F will also set free format, useful when using cobc as a shell interpreter directive to the program loader.
- -fixed Fixed format. Source code is divided into a 1-6 column sequence number area, column 7 indicator area, columns 8-72 program-text area, with columns 72-80 as a reference area. Historically this format is based on 80 character punch cards. FIXED format is the default used by the compiler unless overridden by compiler switch or source code directive, >>SOURCE [FORMAT] [IS] {FIXED|FREE}.

 $<sup>^{2}</sup>$  The extension varies depending on your host.

Chapter 2: Compile 4

## 2.1.4 Warning Options

-W Enable every possible warning. This includes more information than -Wall would normally provide.

-Wall Enable all common warnings

-Warchaic

Warn if archaic features are used

-Wcall-params

Warn non 01/77 items for CALL params (NOT set with -Wall)

-Wcolumn-overflow

Warn if text after column 72 in FIXED format (NOT set with -Wall)

-Wconstant

Warn inconsistent constant

-Wimplicit-define

Warn implicitly defined data items

-Wlinkage

Warn dangling LINKAGE items (NOT set with -Wall)

-Wobsolete

Warn if obsolete features are used

-Wparentheses

Warn lack of parentheses around AND within OR

-Wredefinition

Warn incompatible redefinition of data items

-Wstrict-typing

Warn type mismatch strictly

-Wterminator

Warn lack of scope terminator END-XXX (NOT set with -Wall)

-Wtruncate

Warn possible field truncation (NOT set with -Wall)

-Wunreachable

Warn unreachable statements (NOT set with -Wall)

## 2.1.5 Configuration Options

-std=<dialect>

Compiler uses the given dialect to determine certain compiler features and warnings. See Appendix F [Appendix F], page 44, and config/\*.conf.

-std=cobol2002

COBOL 2002

-std=cobol2014

**COBOL 2014** 

-std=cobol85

COBOL 85

-std=ibm IBM Compatible

-std=mvs MVS Compatible

-acucomment

'|' is treated as inline comment marker

-std=bs2000 BS2000 Compatible Micro Focus Compatible -std=mf -std=acu ACUCOBOL-GT Compatible -std=default When not specified -conf=<file> User defined dialect configuration. See -std= above. See Appendix F [Appendix F], page 44, and config/\*.conf. -cb\_conf=<tag:value> Override a single configuration entry. See Appendix F [Appendix F], page 44. 2.1.6 Debug Switches Enable all run-time error checks. -d will also enable all run-time error checks, useful -debug when using cobc as a shell interpreter directive to the program loader. Produce debugging information in the output. -g -0 Enable optimization of code size and execution speed. See man gcc for details. -02Optimize even more. -0s Optimize for size. Optimizer will favour code size over execution speed. Generate trace code (Executed SECTION/PARAGRAPH) -ftrace -ftraceall Generate trace code (Executed SECTION/PARAGRAPH/STATEMENTS) -fsyntax-only Syntax error checking only; don't emit any output -fdebugging-line Enable debugging lines ('D' in indicator column) -fsource-location Generate source location code (Turned on by -debug or -g) -fimplicit-init Do automatic initialization of the COBOL runtime system -fstack-check PERFORM stack checking (Turned on by -debug or -g) -fnotrunc Do not truncate binary fields according to PICTURE 2.1.7 Miscellaneous Generate and place a program listing into \*.lst -ext <extension> Add default file extension '\*' or '/' in column 1 treated as comment (FIXED only)

```
-fsign=ASCII
           Numeric display sign ASCII (Default on ASCII machines)
-fsign=EBCDIC
           Numeric display sign EBCDIC (Default on EBCDIC machines)
-ffunctions-all
           Allow use of intrinsic functions without FUNCTION keyword
-ffold-copy=LOWER
           Fold COPY subject to lower case (Default no transformation)
-ffold-copy=UPPER
           Fold COPY subject to upper case (Default no transformation)
-save-temps(=<dir>)
           Save intermediate files (default current directory)
```

## 2.2 Multiple Sources

A program often consists of multiple source files. This section describes how to compile multiple source files.

This section also describes how to build a shared library that can be used by any COBOL programs and how to use external libraries from COBOL programs.

## 2.2.1 Static Linking

The easiest way of combining multiple files is to compile them into a single executable.

One way is to specify all files on the command line:

```
$ cobc -x -o prog main.cob subr1.cob subr2.cob
```

Another way is to compile each file with the option -c, and link them at the end. The top-level program must be compiled with the option -x:

```
$ cobc -c subr1.cob
  $ cobc -c subr2.cob
  $ cobc -c -x main.cob
  $ cobc -x -o prog main.o subr1.o subr2.o
You can link C routines as well using either method:
Method 1:
  $ cobc -o prog main.cob subrs.c
Method 2:
  $ cobc -c subrs.c
  $ cobc -c -x main.cob
  $ cobc -x -o prog main.o subrs.o
```

Any number of functions can be contained in a single C file.

The linked programs will be called dynamically; that is, the symbol will be resolved at run time. For example, the following COBOL statement

```
CALL "subr" USING X.
will be converted into an equivalent C code like this:
  int (*func)() = cob_resolve("subr");
  if (func != NULL)
    func (X);
```

With the compiler options -fstatic-call, more efficient code will be generated like this:

```
subr(X);
```

Note that this option is effective only when the called program name is a literal (like CALL "subr".). With a data name (like CALL SUBR.), the program is still called dynamically.

## 2.2.2 Dynamic Linking

There are two methods to achieve this. Method 1 (Using driver program). Compile all programs with the option -m:

```
$ cobc -m main.cob subr.cob
```

This creates shared object files main.so subr.so<sup>3</sup>.

Before running the main program, install the module files in your library directory:

```
$ cp subr.so /your/cobol/lib
```

Set the runtime variable COB\_LIBRARY\_PATH to your library directory, and run the main program:

```
$ export COB_LIBRARY_PATH=/your/cobol/lib
```

Note: You may set the variable via a runtime configuration file, See Appendix H [Appendix H], page 48. You may set the variable to directly point to the directory where you compiled the sources.

Now execute your program:

```
$ cobcrun main
```

Method 2. The main program and subprograms can be compiled separately.

The main program is compiled as usual:

```
$ cobc -x -o main main.cob
```

Subprograms are compiled with the option -m:

```
$ cobc -m subr.cob
```

This creates a module file subr.so<sup>4</sup>.

Before running the main program, install the module files in your library directory:

```
$ cp subr.so /your/cobol/lib
```

Now, set the environment variable COB\_LIBRARY\_PATH to your library directory, and run the main program:

```
$ export COB_LIBRARY_PATH=/your/cobol/lib
```

\$ ./main

### 2.2.3 Building Library

You can build a shared library by combining multiple COBOL programs and even C routines:

```
$ cobc -c subr1.cob
$ cobc -c subr2.cob
$ cc -c subr3.c
$ cc -shared -o libsubrs.so subr1.o subr2.o subr3.o
```

 $<sup>^{3}</sup>$  The extension varies depending on your host.

<sup>&</sup>lt;sup>4</sup> The extension varies depending on your host.

### 2.2.4 Using Library

You can use a shared library by linking it with your main program.

Before linking the library, install it in your system library directory:

```
$ cp libsubrs.so /usr/lib
or install it somewhere else and set LD_LIBRARY_PATH:
    $ cp libsubrs.so /your/cobol/lib
    $ export LD_LIBRARY_PATH=/your/cobol/lib
Then, compile the main program, linking the library as follows:
```

\$ cobc -x main.cob -L/your/cobol/lib -lsubrs

### 2.3 C Interface

This chapter describes how to combine C programs with COBOL programs.

## 2.3.1 Writing Main Program in C

#include <libcob.h>

Include libcob.h in your C program. Call cob\_init before using any COBOL module:

```
int
main (int argc, char **argv)
{
    /* initialize your program */
    ...

    /* initialize the COBOL run-time library */
    cob_init (argc, argv);

    /* rest of your program */
    ...

    /* Clean up and terminate - This does not return */
    cob_stop_run (return_status);
}
```

You can write cobc\_init(0, NULL); if you do not want to pass command line arguments to COBOL.

```
You can compile your C program as follows:
cc -c 'cob-config --cflags' main.c
```

The compiled object must be linked with libcob as follows:

```
cc -o main main.o 'cob-config --libs'
```

## 2.3.2 Static linking with COBOL programs

Let's call the following COBOL module from a C program:

```
---- say.cob -------
IDENTIFICATION DIVISION.
PROGRAM-ID. say.
ENVIRONMENT DIVISION.
DATA DIVISION.
LINKAGE SECTION.
```

```
01 HELLO PIC X(6).
         01 WORLD PIC X(6).
         PROCEDURE DIVISION USING HELLO WORLD.
         DISPLAY HELLO WORLD.
         EXIT PROGRAM.
This program accepts two arguments, displays them, and exits.
From the viewpoint of C, this is equivalent to a function having the following prototype:
  extern int say(char *hello, char *world);
So, your main program will look like as follows:
  ---- hello.c ------
  #include <libcob.h>
  extern int say(char *hello, char *world);
  int
  main()
    int ret;
    char hello[7] = "Hello ";
    char world[7] = "World!";
    cob_init(0, NULL);
    ret = say(hello, world);
    return ret;
         -----
Compile these programs as follows:
  $ cc -c 'cob-config --cflags' hello.c
  $ cobc -c -static say.cob
  $ cobc -x -o hello hello.o say.o
  $ ./hello
  Hello World!
```

### 2.3.3 Dynamic linking with COBOL programs

You can find a COBOL module having a specific PROGRAM-ID by using a C function cob\_resolve, which takes the module name as a string and returns a pointer to the module function.

cob\_resolve returns NULL if there is no module. In this case, the function cob\_resolve\_error returns the error message.

```
Let's see an example:
    --- hello-dynamic.c -----
#include <libcob.h>

static int (*say)(char *hello, char *world);
int
main()
```

```
int ret;
    char hello[7] = "Hello ";
    char world[7] = "World!";
    cob_init(0, NULL);
    /* find the module with PROGRAM-ID "say". */
    say = cob_resolve("say");
    /* if there is no such module, show error and exit */
    if (say == NULL) {
      fprintf(stderr, "%s\n", cob_resolve_error ());
      exit(1);
    }
    /* call the module found and exit with the return code */
    ret = say(hello, world);
    return ret;
Compile these programs as follows:
  $ cc -c 'cob-config --cflags' hello-dynamic.c
  $ cobc -x -o hello hello-dynamic.o
  $ cobc -m say.cob
  $ export COB_LIBRARY_PATH=.
  $ ./hello
  Hello World!
```

### 2.3.4 Static linking with C programs

Let's call the following C function from COBOL:

```
int
say(char *hello, char *world)
{
  int i;
  for (i = 0; i < 6; i++)
    putchar(hello[i]);
  for (i = 0; i < 6; i++)
    putchar(world[i]);
  putchar('\n');
  return 0;
}</pre>
```

This program is equivalent to the foregoing say.cob.

Note that, unlike C, the arguments passed from COBOL programs are not terminated by the null character (i.e.,  $\setminus 0$ ).

You can call this function in the same way you call COBOL programs:

```
---- hello.cob ------
```

```
IDENTIFICATION DIVISION.

PROGRAM-ID. hello.

ENVIRONMENT DIVISION.

DATA DIVISION.

WORKING-STORAGE SECTION.

01 HELLO PIC X(6) VALUE "Hello ".

01 WORLD PIC X(6) VALUE "World!".

PROCEDURE DIVISION.

CALL "say" USING HELLO WORLD.

STOP RUN.
```

Y 11 (1 C 11

Compile these programs as follows:

```
$ cc -c say.c
$ cobc -c -static -x hello.cob
$ cobc -x -o hello hello.o say.o
$ ./hello
Hello World!
```

## 2.3.5 Dynamic linking with C programs

You can create a dynamic-linking module from a C program by passing an option -shared to the C compiler:

```
$ cc -shared -o say.so say.c
$ cobc -x hello.cob
$ export COB_LIBRARY_PATH=.
$ ./hello
Hello World!
```

## 3 Customize

## 3.1 Customizing Compiler

These settings are effective at compile-time.

Environment variables (default value):

COB\_CC C compiler ("gcc")

COB\_CFLAGS

Flags passed to the C compiler ("-I\$(PREFIX)/include")

COB\_LDFLAGS

Flags passed to the C compiler ("")

COB\_LIBS Standard libraries linked with the program ("-L\$(PREFIX)/lib -lcob")

COB\_LDADD

Additional libraries linked with the program ("")

## 3.2 Customizing Library

These settings are effective at run-time. You can set them either via environment or by a runtime configuration file.

To set global runtime configuration file export COB\_RUNTIME\_CONFIG pointing to your configuration file. To set an explicit runtime configuration file for a single run via cobcrun you can use its option -c <file>, -config=<file>.

For diplaying the current runtime settings you can use the option -r, -runtime-env of cobcrun.

For a complete list of runtime variables, aliases, their default values and options to set them See Appendix H [Appendix H], page 48.

## 4 Optimize

## 4.1 Optimize Options

There are three compiler options for optimization: -0, -0s and -02. These options enable optimization at both translation (from COBOL to C) and compilation (C to assembly) levels.

Currently, there is no difference between these optimization options at the translation level. The option -0, -0s or -02 is passed to the C compiler as it is and used for C level optimization.

## 4.2 Optimize Call

When a CALL statement is executed, the called program is linked at run time. By specifying the compiler option -fstatic-call, you can statically link the program at compile time and call it efficiently. (see Section 2.2.1 [Static Linking], page 6)

## 4.3 Optimize Binary

By default, data items of usage binary or comp are stored in the big-endian form. On those machines whose native byte order is little-endian, this is not quite efficient.

If you prefer, you can store binary items in the native form of your machine. Set the config option binary-byteorder to native in your config file (see Chapter 3 [Customize], page 12).

In addition, setting the option binary-size to 2-4-8 or 1-2-4-8 is more efficient than others.

Chapter 5: Debug

## 5 Debug

## 5.1 Debug Options

The compiler option <code>-debug</code> can be used during the development of your programs. It enables all run-time error checking, such as subscript boundary checks and numeric data checks, and displays run-time errors with source locations.

## 6 Extensions not ISO/ANSI standard

### 6.1 SELECT ASSIGN TO

<This section is in progress.>

## 6.2 Indexed file packages

<This section is in progress.>

## 6.3 Extended ACCEPT statement

Extended ACCEPT statements allow for full control of items accepted from the screen. Items accept by line and column positioning.

```
ACCEPT variable-1

LINE <line> COLUMN <column>
WITH

AUTO-SKIP | AUTO

[PROTECTED] SIZE [IS] variable-2 | literal-2
END-ACCEPT.
```

### **6.3.1 AUTO-SKIP**

With this option the ACCEPT statement returns after the last character is typed at the end of the field. This is the same as if the Enter key were pressed.

Without this option the cursor remains at the end of the field and waits for the user to press Enter.

The word AUTO may be used for AUTO-SKIP.

The Right-Arrow key returns from the end of the field. The Left-Arrow key returns from the beginning. See Section 6.4 [ACCEPT Special], page 16.

The Alt-Right-Arrow and Alt-Left-Arrow keys never AUTO-SKIP.

## 6.3.2 PROTECTED

PROTECTED is ignored. It is optional.

### 6.3.3 SIZE

The size of variable-1 to accept from the screen. It is optional.

### SIZE <greater than zero>

If SIZE is less than the length of variable-1 then only the SIZE number of characters accept into the field. Variable-1 pads with spaces after SIZE to the end of the field.

If SIZE is greater than variable-1, then the screen pads with spaces after variable-1 to the SIZE length.

#### SIZE ZERO

### <SIZE option not specified>

The variable-1 field accepts with its length.

## 6.4 ACCEPT special keys

Special keys are available for Extended ACCEPT statements.

The COB-CRT-STATUS values are in the screenio.cpy copy file.

### 6.4.1 Arrow keys

The Left-Arrow key moves the cursor to the left. Without AUTO-SKIP the cursor stops at the beginning of the field. With AUTO-SKIP it returns with the COB-SCR-KEY-LEFT value of 2009. See Section 6.3 [Extended ACCEPT], page 15.

The Alt-Left-Arrow key is the same as Left-Arrow except that it never returns, even for AUTO-SKIP.

The Right-Arrow key moves the cursor to the right. Without AUTO-SKIP the cursor stops at the end of the field. With AUTO-SKIP it returns with the COB-SCR-KEY-RIGHT value of 2010. See Section 6.3 [Extended ACCEPT], page 15.

The Alt-Right-Arrow key is the same as Right-Arrow except that it never returns, even for AUTO-SKIP.

## 6.4.2 Backspace key

The Backspace key moves the cursor, and the remainder of the text, to the left.

## 6.4.3 Delete keys

The Delete key deletes the cursor's character and moves the remainder of the text to the left. The cursor does not move.

The Alt-Delete key deletes all text from the cursor to the end of the field.

### 6.4.4 End keys

The End key moves the cursor after the last non-space character.

The Alt-End key moves the cursor to the end of the field.

### 6.4.5 Home keys

The Home key moves the cursor to the first non-space character.

The Alt-Home key moves the cursor to the beginning of the field.

### 6.4.6 Insert key

The Insert key changes the insert mode.

When the insert mode is on, typed characters move the existing characters to the right. When it is off, typed characters type over existing characters.

The default insert mode is set by the COB\_INSERT\_MODE variable, See Appendix H [Appendix H], page 48. This must be set before the first Extended ACCEPT, DISPLAY, or any routine that gets information from the screen.

The last press of the Insert key is used in all following ACCEPT statements while the program is running.

### **6.4.7** Tab keys

The Tab key returns from the ACCEPT with the COB-SCR-TAB value of 2007.

The Shift-Tab key returns with the COB-SCR-BACK-TAB value of 2008.

### 6.5 Extended DISPLAY statement

Extended DISPLAY statements allow for full control of items that display on the screen. Items display by line and column positioning.

```
DISPLAY variable-1 | literal-1 | figurative constant
LINE <line> COLUMN <column>
WITH BELL
BLANK LINE | SCREEN
ERASE EOL | EOS
SIZE [IS] variable-2 | literal-2
END-DISPLAY.
```

### 6.5.1 BELL

Ring the bell. It is optional.

### 6.5.2 BLANK

Clear the whole line or screen. It is optional.

BLANK LINE

Clear the line from the beginning of the line to the end of the line.

BLANK SCREEN

Clear the whole screen.

### 6.5.3 ERASE

Clear the line or screen from LINE and COLUMN. It is optional.

ERASE EOL

Clear the line from LINE and COLUMN to the end of the line.

ERASE EOS

Clear the screen from LINE and COLUMN to the end of the screen.

#### 6.5.4 SIZE

The size of variable-1, literal-1, or figurative constant to display onto the screen. It is optional.

### SIZE <greater than zero>

If SIZE is less than the length of variable-1 or literal-1 then only the SIZE number of characters display.

If SIZE is greater than the length of variable-1 or literal-1, then the screen pads with spaces after the field to the SIZE length.

Figurative constants display repeatedly the number of times in SIZE. Except that LOW-VALUES always positions the cursor (see SIZE ZERO below).

SIZE ZERO

### <SIZE option not specified>

Variable-1 or literal-1 displays with the field length.

Certain figurative constants have special functions.

SPACE Display spaces from LINE and COLUMN to the end of the screen. This is the same as WITH ERASE EOS.

LOW-VALUE Position the cursor to LINE and COLUMN. The next DISPLAY statement does not need a LINE or COLUMN to display at that position.

ALL "1" Display spaces from LINE and COLUMN to the end of the line. This is the same as WITH ERASE EOL.

ALL "2" Clear the whole screen. This is the same as WITH BLANK SCREEN.

ALL "7" Ring the bell. This is the same as WITH BELL.

All other figurative constants display as a single character.

## 7 System routines

For a complete list of supported system routines See Appendix D [cobc –list-system], page 39.

## 7.1 CBL\_OC\_GETOPT

CBL\_OC\_GETOPT realises the quite well-known option parser getopt for GnuCOBOL. The usage of this system routine is described by the following example.

```
identification division.
program-id. prog.
data division.
working-storage section.
    78 shortoptions value "jkl".
   01 longoptions.
        05 optionrecord occurs 2 times.
            10 optionname pic x(25).
            10 has-value
                           pic 9.
            10 valpoint
                            pointer value NULL.
            10 return-value pic x(4).
   01 longind
                   pic 99.
    01 long-only
                  pic 9 value 1.
    01 return-char pic x(4).
    01 opt-val
                  pic x(10).
    01 counter
                  pic 9 value 0.
```

We first need to define the necessary fields for getopt's shortoptions (so), longoptions (lo), longoption index (longind), long-only-option (long-only) and also the fields for return values return-char and opt-val (arbitrary size with trimming, see return codes).

The shortoptions are written down as an alphanumeric field (string with arbitrary size) as follows:

```
"ab:c::d"
```

This means we want getopt to look for shortoptions named a, b, c or d and we demand an option value for b and we are accepting an optional one for c.

The longoptions are defined as a table of records with oname, has-value, valpoint and val. The field oname defines the name of a longoption, has-value defines if an option value is demanded(has-val = 1), optional(2) or not required(0).

The longoption structure is immutable! You can vary the amount of records only. The pointer valpoint is used to specify an address to save getopt's return value to. The pointer is optional.

If it is NULL, getopt returns a value as usual. If you use the pointer it has to point to a PIC X(4) field.

The field val is a PIC X(4) character which is returned if the longoption was recognized.

Now we have the tools to run CBL\_OC\_GETOPT within the procedure division.

```
procedure division.
   move "version" to optionname
                                   (1).
   move 0
                 to has-value
                                   (1).
   move "v"
                  to return-value (1).
   move "verbose" to optionname
                                   (2).
   move 0
             to has-value
                                   (2).
   move "V"
                  to return-value (2).
   perform with test after until return-code = -1
        call 'CBL_OC_GETOPT' using
           by reference shortoptions longoptions longind
          by value long-only
           by reference return-char opt-val
        end-call
        display return-char end-display
        display opt-val end-display
    end-perform
    stop run.
```

The example shows how we initialize all parameters and call the routine until as CBL\_OC\_GETOPT doesn't find any option, returning '-1' in this case.

The return-char might contain the following:

- regular character if an option was recognized
- '?' if we have got an undefined or ambiguous option
- '1' if got a non-option (only if first byte of so is '-')
- '0' if valpoint != NULL and we are writing the return value to the specified address
- '-1' if we don't have any more options (or reach the first non-option if first byte of so is '+')

The return-codes of CBL\_OC\_GETOPT are:

- 1 if we've got a non-option (only if first byte of so is '-')
- 0 if valpoint != NULL and we are writing the return value to the specified address
- -1 if we don't have any more options (or reach the first non-option if first byte of so is '+')
- 2 if we have got an truncated option value in opt-val (because opt-val was too small)
- 3 if we got a regular answer from getopt

## Appendix A cobc --help

Usage: /d/Programme/Entwicklung/GnuCOBOL/gnu-cobol-2.0\_ultraclean2/cobc/.libs/cobc [options]

GnuCOBOL compiler for most COBOL dialects with lots of extensions

```
Options:
 -h, -help
                        Display this help and exit
 -V, -version
                        Display compiler version and exit
 -i, -info
                        Display compiler information (build/environment)
  -v, -verbose
                        Display the commands invoked by the compiler
                        Display compiler version and display the commands
  -vv
                        invoked by the compiler
                        Build an executable program
  -x
                        Build a dynamically loadable module (default)
  -m
                        Run job, after build
  -j
  -std=<dialect>
                        Warnings/features for a specific dialect:
                          cobol2002 COBOL 2002
                          cobol2014 COBOL 2014
                          cobol85 COBOL 85
                          ibm
                                     IBM Compatible
                                     MVS Compatible
                          mvs
                                    BS2000 Compatible
                          bs2000
                          mf
                                     Micro Focus Compatible
                                     ACUCOBOL-GT Compatible
                          acu
                          default When not specified
                        See config/default.conf and config/*.conf
 -free
                        Use free source format
  -fixed
                        Use fixed source format (default)
                        Alias (short option) for -free
 -0, -02, -0s
                        Enable optimization
                        Enable C compiler debug / stack check / trace
  -g
  -d, -debug
                        Enable all run-time error checking
  -o <file>
                        Place the output into <file>
                        Combine all input files into a single
  -b
                        dynamically loadable module
                        Preprocess only; do not compile or link
  -E
  -C
                        Translation only; convert COBOL to C
  -S
                        Compile only; output assembly file
                        Compile and assemble, but do not link
  -P(=<dir or file>)
                        Generate preprocessed program listing (.lst)
                        Generate cross reference through 'cobxref'
  -Xref
                        (V. Coen's 'cobxref' must be in path)
 -I <directory>
                        Add <directory> to copy/include search path
 -L <directory>
                        Add <directory> to library search path
 -1 <lib>
                        Link the library <lib>
                        Add <options> to the C compile phase
 -A <options>
 -Q <options>
                        Add <options> to the C link phase
 -D <define>
                        DEFINE <define> to the COBOL compiler
  -K <entry>
                        Generate CALL to <entry> as static
  -conf=<file>
                        User defined dialect configuration - See -std=
  -cb_conf=<tag:value> Override configuration entry
```

-list-reserved Display reserved words
-list-intrinsics Display intrinsic functions
-list-mnemonics Display mnemonic names
-list-system Display system routines
-save-temps(=<dir>) Save intermediate files

- Default : current directory

-ext <extension> Add default file extension

-W Enable ALL warnings

-Wall Enable all warnings except as noted below

-Wobsolete Warn if obsolete features are used -Warchaic Warn if archaic features are used

-Wredefinition Warn incompatible redefinition of data items

-Wconstant Warn inconsistent constant
-Woverlap Warn overlapping MOVE items

-Wparentheses Warn lack of parentheses around AND within OR

-Wstrict-typing Warn type mismatch strictly

-Wimplicit-define Warn implicitly defined data items

-Wcorresponding Warn CORRESPONDING with no matching items
-Wexternal-value Warn EXTERNAL item with VALUE clause
-Wcall-params Warn non 01/77 items for CALL params

- NOT set with -Wall

-Wcolumn-overflow Warn text after column 72, FIXED format

- NOT set with -Wall

-Wterminator Warn lack of scope terminator END-XXX

- NOT set with -Wall

-Wtruncate Warn possible field truncation

- NOT set with -Wall

-Wlinkage Warn dangling LINKAGE items

- NOT set with -Wall

-Wunreachable Warn unreachable statements

- NOT set with -Wall

-fsign=<value> Define display sign representation

- ASCII or EBCDIC (Default : machine native)

-ffold-copy=<value> Fold COPY subject to value

- UPPER or LOWER (Default : no transformation)

-ffold-call=<value> Fold PROGRAM-ID, CALL, CANCEL subject to value

- UPPER or LOWER (Default : no transformation)

-fdefaultbyte=<value> Initialize fields without VALUE to decimal value

- 0 to 255 (Default : initialize to picture)
-fintrinsics=<value> Intrinsics to be used without FUNCTION keyword

- ALL or intrinsic function name (,name,...)

-ftrace Generate trace code

- Executed SECTION/PARAGRAPH

-ftraceall Generate trace code

- Executed SECTION/PARAGRAPH/STATEMENTS

- Turned on by -debug

-fsyntax-only Syntax error checking only; don't emit any output

-fdebugging-line Enable debugging lines

- 'D' in indicator column or floating >>D

-fsource-location Generate source location code

- Turned on by -debug/-g/-ftraceall

-fimplicit-init Automatic initialization of the Cobol runtime system

-fstack-check PERFORM stack checking

- Turned on by -debug or -g

-fsyntax-extension Allow syntax extensions

- eg. Switch name SW1, etc.

-fwrite-after Use AFTER 1 for WRITE of LINE SEQUENTIAL

- Default : BEFORE 1

-fmfcomment '\*' or '/' in column 1 treated as comment

- FIXED format only

-facucomment '\$' in indicator area treated as '\*',

 $\mbox{'}\mbox{|'}$  treated as floating comment

-fnotrunc Allow numeric field overflow

- Non-ANSI behaviour

-fodoslide Adjust items following OCCURS DEPENDING

- Requires implicit/explicit relaxed syntax

-fsingle-quote Use a single quote (apostrophe) for QUOTE

- Default : double quote

-frecursive-check Check recursive program call

-frelax-syntax Relax syntax checking

- eg. REDEFINES position

-foptional-file Treat all files as OPTIONAL

- unless NOT OPTIONAL specified

# Appendix B cobc --list-reserved

Reserved Words	Implemented (Y/N)
ACCEPT	Y
ACCESS	Y
ACTIVE-CLASS	N
ADD	Y
ADDRESS	Y
ADVANCING	Y
AFTER.	Y
ALIGNED	N
ALL	Y
ALLOCATE	Y
ALPHABET	Y
ALPHABETIC	Y
ALPHABETIC-LOWER	Y
ALPHABETIC-UPPER	Y
ALPHANUMERIC	Y
ALPHANUMERIC-EDITED	Y
ALSO	Y
ALTER	Y
ALTERNATE	Υ
AND	Υ
ANY	Y
ANYCASE	N
ARE	Υ
AREA	Υ
AREAS	Υ
ARGUMENT-NUMBER	Υ
ARGUMENT-VALUE	Υ
ARITHMETIC	N (Context sensitive)
AS	Y
ASCENDING	Y
ASCII	Y (Context sensitive)
ASSIGN	Y
AT	Y
ATTRIBUTE	Y (Context sensitive)
AUTO	Y
AUTO-SKIP	Y
AUTOMATIC	Y
AUTOTERMINATE	Y
AWAY-FROM-ZERO	Y (Context sensitive)
B-AND	N
B-NOT	N
B-OR	N
B-XOR	N 
BACKGROUND-COLOR	Y
BACKGROUND-COLOUR	Y
BASED	Υ
BEEP	Y

BEFORE	Y	
BELL	Y	
BINARY	Y	
BINARY-C-LONG	Y	
BINARY-CHAR	Y	
BINARY-DOUBLE	Y	
BINARY-INT	Y	
BINARY-LONG	Y	
BINARY-LONG-LONG	Y	
BINARY-SHORT	Y	
BIT	N	
BLANK	Y	
BLINK	Y	
BLOCK	Y	
BOOLEAN	N	
BOTTOM	Y	
BY	Y	
BYTE-LENGTH	Y	(Context sensitive)
CALL	Y	(Oonteat Benditive)
CANCEL	Y	
CAPACITY	Y	(Context sensitive)
CD	N	
CENTER	N	(Context sensitive)
CF	Y	(Context Sensitive)
CH	Y	
CHAIN	N	
CHAINING	Y	
CHARACTER	Y	
CHARACTERS	Y	
CLASS	Y	
CLASS-ID	N	
CLASSIFICATION	Y	(Context sensitive)
CLOSE	Y	(Concext Sensitive)
CODE	Y	
CODE-SET	Y	
COL COL	Y	
COLLATING	Y	
COLS	Y	
	Y	
COLUMN COLUMNS	Y	
COMMA	Y	
COMMAND-LINE	Y	
	Y	
COMMIT	Y	
		(OF abaalata)
COMMUNICATION	N	(85 obsolete)
COMP	Y	
COMP-1	Y	
COMP 2	Y	
COMP 4	Y	
COMP-4	Y	
COMP-5	Y	
COMP-6	Y	

COMP-X	Y
COMPUTATIONAL	Y
COMPUTATIONAL-1	Y
COMPUTATIONAL-2	Y
COMPUTATIONAL-3	Y
COMPUTATIONAL-4	Υ
COMPUTATIONAL-5	Υ
COMPUTATIONAL-X	Y
COMPUTE	Y
CONDITION	Y
CONFIGURATION	Υ
CONSTANT	Υ
CONTAINS	Y
CONTENT	Y
CONTINUE	Y
CONTROL	Y
CONTROLS	Y
CONVERSION	Y (Context sensitive)
	- (,
CONVERTING	Y
COPY	Y
CORR	Υ
CORRESPONDING	Y
COUNT	Y
CRT	Y
CRT-UNDER	Y
CURRENCY	Y
CURSOR	Y
CYCLE	Y (Context sensitive)
DATA	Y
DATA-POINTER	N
DATE	Y
DAY	Y
DAY-OF-WEEK	Y
DE	Y
DEBUGGING	Υ
DECIMAL-POINT	Y
DECLARATIVES	Y
DEFAULT	Y
DELETE	Y
DELIMITED	Y
DELIMITER	Y
DEPENDING	Y
DESCENDING	Y
DESTINATION	N
DETAIL	Y
DISABLE	N W (G · · · · · · · · · · · · · · · · · ·
DISC	Y (Context sensitive)
DISK	Y (Context sensitive)
DISPLAY	Y
DIVIDE	Y
DIVISION	Y
DOWN	Υ

DUPLICATES	Y	
DYNAMIC	Y	
EBCDIC	Y	(Context sensitive)
EC	Y	(Concest Sensitive)
EGI	N	(85 obsolete)
ELSE	Y	(00 Obsolete)
EMI	N	(85 obsolete)
EMPTY-CHECK	Y	(OO ODSOIECE)
ENABLE	N	(85 obsolete)
END	Y	(OO ODBOIECE)
END-ACCEPT	Y	
END-ADD	Y	
END-CALL	Y	
END-CHAIN	N	
END-COMPUTE	Y	
END-DELETE	Y	
END-DISPLAY	Y	
END-DISTERT END-DIVIDE	Y	
END-EVALUATE	Y	
END-IF	Y	
END-MULTIPLY	Y	
END-OF-PAGE	Y	
END-PERFORM	Y	
END-READ	Y	
END-RECEIVE	N	(85 obsolete)
END-RETURN	Y	(OO ODBOIECE)
END-REWRITE	Y	
END-SEARCH	Y	
END-START	Y	
END-STRING	Y	
END-SUBTRACT	Y	
END-UNSTRING	Y	
END-WRITE	Y	
ENTRY	Υ	
ENTRY-CONVENTION	N	(Context sensitive)
ENVIRONMENT	Y	(Context Bensitive)
ENVIRONMENT-NAME	Y	
ENVIRONMENT-VALUE	Y	
EO	N	
EOL	Y	(Context sensitive)
EOP	Y	(CONTOCAT DENDITORY)
EOS	Y	(Context sensitive)
EQUAL	Y	(CONTOCAT DENDITORY)
EQUALS	Y	
ERASE	Y	
ERROR	Y	
ESCAPE	Y	
ESI	N	(85 obsolete)
EVALUATE	Y	(OO ODDOTERE)
EXCEPTION	Y	
EXCEPTION-OBJECT	N	
EXCLUSIVE	Y	
	1	

EXIT	Y		
EXPANDS	N	(Context	sensitive)
EXTEND	Y		
EXTERNAL	Y		
FACTORY	N		
FALSE	Y		
FD	Y		
FILE	Y		
FILE-CONTROL	Y		
FILE-ID	Y		
FILLER	Y		
FINAL	Y		
FIRST	Y		
FLOAT-BINARY-128	N		
FLOAT-BINARY-32	N		
FLOAT-BINARY-64	N		
FLOAT-DECIMAL-16	Y		
FLOAT-DECIMAL-34	Y		
FLOAT-EXTENDED	N		
FLOAT-INFINITY	N		
FLOAT-LONG	Y		
FLOAT-NOT-A-NUMBER	N	(Context	sensitive)
FLOAT-SHORT	Y	COHOCAG	DOIDI GIVO)
FOOTING	Y		
FOR	Y		
FOREGROUND-COLOR	Y		
FOREGROUND-COLOUR	Y		
FOREVER	Y		
FORMAT	N		
FREE	Y		
FROM	Y		
FULL	Y		
FUNCTION ID	Y		
FUNCTION-ID	Y		
FUNCTION-POINTER	N		
GENERATE	Y		
GET	N		
GIVING	Y		
GLOBAL	Y		
GO GODAGY	Y		
GOBACK	Y		
GREATER	Y		
GROUP	Y		
GROUP-USAGE	N		
HEADING	Y		
HIGH-VALUE	Y		
HIGH-VALUES	Y		
HIGHLIGHT	Y		
I-0	Y		
I-O-CONTROL	Y		
ID	Y		
IDENTIFICATION	Y		

IF	Y		
IGNORE	Y		
IGNORING	Y		
IMPLEMENTS	N	(Context	sensitive)
IN	Y	(002200210	2011210110,
INDEX	Y		
INDEXED	Y		
INDICATE	Y		
INDIRECT	N	(Context	sensitive)
INHERITS	N	(002200210	2011210110,
INITIAL	Y		
INITIALISE	Y		
INITIALISED	Y		
INITIALIZE	Y		
INITIALIZED	Y		
INITIATE	Y		
INPUT	Y		
INPUT-OUTPUT	Y		
INSPECT	Y		
INTERFACE	N		
INTERFACE-ID	N		
INTERMEDIATE	N	(Context	sensitive)
INTO	Y	(002200210	2011210110,
INTRINSIC	Y	(Context	sensitive)
INVALID	Y	(	
INVOKE	N		
IS	Y		
JUST	Y		
JUSTIFIED	Y		
KEPT	Y		
KEY	Y		
KEYBOARD	Y	(Context	sensitive)
LABEL	Y	•	
LAST	Y		
LC_ALL		(Context	sensitive)
LC_COLLATE			sensitive)
LC_CTYPE			sensitive)
LC_MESSAGES			sensitive)
LC_MONETARY			sensitive)
LC_NUMERIC	N		sensitive)
LC_TIME	N		sensitive)
LEADING	Y		
LEFT	Y		
LEFT-JUSTIFY	N		
LEFTLINE	Y		
LENGTH	Y		
LENGTH-CHECK	Y		
LESS	Y		
LIMIT	Y		
LIMITS	Y		
LINAGE	Y		
LINAGE-COUNTER	Y		

LINE	Y	
LINE-COUNTER	Y	
LINES	Y	
LINKAGE	Y	
LOCAL-STORAGE	Y	
LOCALE	Y	
LOCK	Y	
LOW-VALUE	Y	
LOW-VALUES	Y	
LOWER	Y	(Context sensitive)
LOWLIGHT	Y	
MANUAL	Y	
MEMORY	Y	
MERGE	Y	
MESSAGE	N	(85 obsolete)
METHOD	N	(66 65561666)
METHOD-ID	N	
MINUS	Y	
	Y	
MODE	_	
MOVE	Y	
MULTIPLE	Y	
MULTIPLY	Y	(a
NAME	Y	(Context sensitive)
NATIONAL	Y	
NATIONAL-EDITED	Y	
NATIVE	Y	
NEAREST-AWAY-FROM-ZERO	Y	(Context sensitive)
NEAREST-EVEN	Y	(Context sensitive)
NEAREST-TOWARD-ZERO	Y	(Context sensitive)
NEGATIVE	Y	
NESTED	N	
NEXT	Y	
NO	Y	
NO-ECHO	Y	
NONE	N	(Context sensitive)
NORMAL	Y	(Context sensitive)
NOT	Y	
NULL	Y	
NULLS	Y	
NUMBER	Y	
NUMBERS	Y	
NUMERIC	Y	
NUMERIC-EDITED	Y	
OBJECT	N	
OBJECT-COMPUTER	Y	
	N	
OBJECT-REFERENCE		
OCCURS	Y	
OF OFF	Y	
OFF	Y	
OMITTED	Y	
ON	Y	
ONLY	Y	

OPEN	Υ
OPTIONAL	Y
OPTIONS	N
OR	Y
ORDER	Y
ORGANISATION	Y
ORGANIZATION	Y
OTHER	Y
OUTPUT	Y
OVERFLOW	Y
OVERLINE	Y
OVERRIDE	N
PACKED-DECIMAL	Y
PADDING	Y
PAGE	Y
PAGE-COUNTER	Y
PARAGRAPH	Y (Context sensitive)
PERFORM	Υ
PF	Υ
РН	Υ
PIC	Y
PICTURE	Y
PLUS	Y
POINTER	Y
POSITION	Y
POSITIVE	Y
PREFIXED	N (Context sensitive)
PRESENT	Y
PREVIOUS	Y
PRINTER	Y (Context sensitive)
PRINTING	Y
PROCEDURE	Y
PROCEDURE-POINTER	Y
PROCEDURES	Y
PROCEED	Y
PROGRAM	Y
PROGRAM-ID	Y
PROGRAM-POINTER	Y
PROHIBITED	Y (Context sensitive)
PROMPT	Y
PROPERTY	N
PROTECTED	Y
PROTOTYPE	N
PURGE	N (85 obsolete)
QUEUE	N (85 obsolete)
QUOTE	Y
QUOTES	Υ
RAISE	N
RAISING	N
RANDOM	Υ
RD	Y
READ	Υ

```
RECEIVE
                                  N (85 obsolete)
RECORD
                                  Y
RECORDING
                                  Y
RECORDS
                                  Y
RECURSIVE
                                  Y (Context sensitive)
REDEFINES
                                  Y
REEL
                                  Y
REFERENCE
                                  Y
REFERENCES
                                  Y
RELATION
                                  N (Context sensitive)
RELATIVE
                                  Y
                                  Y
RELEASE
REMAINDER
                                  Y
REMOVAL
                                  Y
RENAMES
                                  Y
REPLACE
                                  Y
REPLACING
                                  Y
REPORT
                                  Y
REPORTING
                                  Y
REPORTS
                                  Y
REPOSITORY
                                  Y
REQUIRED
                                  Y
RESERVE
                                  Y
RESET
                                  Y
RESUME
                                  N
RETRY
                                  N
RETURN
RETURNING
                                  Y
REVERSE-VIDEO
                                  Y
REVERSED
                                  Y
REWIND
                                  Y
REWRITE
                                  Y
RF
                                  Y
RH
                                  Y
RIGHT
                                  Y
RIGHT-JUSTIFY
                                  N
ROLLBACK
                                  Y
ROUNDED
                                  Y
ROUNDING
                                  N (Context sensitive)
RUN
                                  Y
{\tt SAME}
                                  Y
SCREEN
SCROLL
                                  Y (Context sensitive)
SD
SEARCH
                                  Y
SECONDS
                                  N (Context sensitive)
SECTION
                                  Y
SECURE
                                  Y
SEGMENT
                                  N (85 obsolete)
SEGMENT-LIMIT
                                  Y
SELECT
                                  Y
SELF
                                  N
```

		(27)
SEND	N	(85 obsolete)
SENTENCE	Y	
SEPARATE	Y	
SEQUENCE	Y	
SEQUENTIAL	Y	
SET	Y	
SHARING	Y	
SIGN	Y	
SIGNED	Y	
SIGNED-INT	Y	
SIGNED-LONG	Y	
SIGNED-SHORT	Y	
SIZE	Y	
SORT	Y	
SORT-MERGE	Y	
SOURCE	Y	
SOURCE-COMPUTER	Y	
SOURCES	N	
SPACE	Y	
SPACE-FILL	N	
SPACES	Y	
SPECIAL-NAMES	Y	
STANDARD	Y	
STANDARD-1	Y	
STANDARD-2	Y	
STANDARD-BINARY	N	(Context sensitive)
STANDARD-DECIMAL	N	(Context sensitive)
START	Y	
STATEMENT	N	(Context sensitive)
STATIC	Y	(Context sensitive)
STATUS	Y	
STDCALL	Y	(Context sensitive)
STEP	Y	
STOP	Y	
STRING	Y	
STRONG	N	••••••
SUB-QUEUE-1		(85 obsolete)
SUB-QUEUE-2	N	(85 obsolete)
SUB-QUEUE-3	N	(85 obsolete)
SUBTRACT	Y	
SUM	Y	
SUPER	N	
SUPPRESS	Y	
SYMBOL	N	(Context sensitive)
SYMBOLIC	Y	
SYNC	Y	
SYNCHRONISED	Y	
SYNCHRONIZED	Y	
SYSTEM-DEFAULT	Y	
TAB	Y	(Context sensitive)
TABLE	N	
TALLYING	Y	

TAPE	Y	(Context sensitive)
TERMINAL	N	(85 obsolete)
TERMINATE	Y	(op opposere)
TEST	Y	
TEXT	N	(85 obsolete)
THAN	Υ	(OO ODSOIECE)
THEN	Y	
THROUGH	Y	
THRU	Y	
TIME	Y	
TIME-OUT	Y	(Contout gongitius)
TIMEOUT	Y	(Context sensitive) (Context sensitive)
TIMES	Y	(Context Sensitive)
TO	Y	
TOP	Y	
	Υ	(Contout consitius)
TOWARD-GREATER TOWARD-LESSER	Y	(Context sensitive) (Context sensitive)
TRAILING	Y	(Context Sensitive)
	_	
TRAILING-SIGN	N	
TRANSFORM	Y	
TRUE	Y	(0
TRUNCATION	Y	(Context sensitive)
TYPE	Y	
TYPEDEF	N	(0
UCS-4	N	(Context sensitive)
UNDERLINE	Y	
UNIT	Y	
UNIVERSAL	N	
UNLOCK	Y	
UNSIGNED	Y	
UNSIGNED-INT	Y	
UNSIGNED-LONG	Y	
UNSIGNED-SHORT	Y	
UNSTRING	Y	
UNTIL	Y	
UP	Y	
UPDATE	Y	
UPON	Y	
UPPER	Y	(Context sensitive)
USAGE	Y	
USE	Y	
USER	Y	(Context sensitive)
USER-DEFAULT	Y	
USING	Y	
UTF-16	N	(Context sensitive)
UTF-8	N	(Context sensitive)
VAL-STATUS	N	
VALID	N	
VALIDATE	N	
VALIDATE-STATUS	N	
VALUE	Y	
VALUES	Y	

VARYING Y
WAIT Y
WHEN Y
WITH Y
WORDS Y
WORKING-STORAGE Y
WRITE Y

YYYYMDDD Y (Context sensitive)
YYYYMMDD Y (Context sensitive)

ZERO Y
ZERO-FILL N
ZEROES Y
ZEROS Y

Extra (obsolete) context sensitive words

AUTHOR

DATE-COMPILED
DATE-MODIFIED
DATE-WRITTEN
INSTALLATION
REMARKS
SECURITY

Extra internal registers Definition

RETURN-CODE USAGE BINARY-LONG SORT-RETURN USAGE BINARY-LONG NUMBER-OF-CALL-PARAMETERS USAGE BINARY-LONG

COB-CRT-STATUS PIC 9(4)

TALLY GLOBAL PIC 9(5) USAGE BINARY VALUE ZERO

'LENGTH OF' phrase USAGE BINARY-LONG

# Appendix C cobc --list-intrinsics

Totalogical Properties	T 7 + 4	D
Intrinsic Function	Implemented	
ABS	Y	1
ACOS	Y	1
ANNUITY	Y	2
ASIN	Y	1
ATAN	Y	1
BOOLEAN-OF-INTEGER	N	2
BYTE-LENGTH	Y	1
CHAR	Y	1
CHAR-NATIONAL	N	1
COMBINED-DATETIME	Y	2
CONCATENATE	Y	Unlimited
COS	Y	1
CURRENCY-SYMBOL	Y	0
CURRENT-DATE	Y	0
DATE-OF-INTEGER	Y	1
DATE-TO-YYYYMMDD	Y	1 - 3
DAY-OF-INTEGER	Y	1
DAY-TO-YYYYDDD	Y	1 - 3
DISPLAY-OF	N	1 - 2
E	Y	0
EXCEPTION-FILE	Y	0
EXCEPTION-FILE-N	N	0
EXCEPTION-LOCATION	Υ	0
EXCEPTION-LOCATION-N	N	0
EXCEPTION-STATEMENT	Υ	0
EXCEPTION-STATUS	Y	0
EXP	Υ	1
EXP10	Y	1
FACTORIAL	Y	1
FORMATTED-CURRENT-DATE	Y	1
FORMATTED-DATE	Y	2
FORMATTED-DATETIME	Y	3 - 4
FORMATTED-TIME	Y	2 - 3
FRACTION-PART	Y	1
HIGHEST-ALGEBRAIC	Y	1
INTEGER	Y	1
INTEGER-OF-BOOLEAN	N	1
INTEGER-OF-DATE	Υ	1
INTEGER-OF-DAY	Y	1
INTEGER-OF-FORMATTED-DATE	Υ	2
INTEGER-PART	Υ	1
LENGTH	Y	1
LENGTH-AN	Y Y	1
	Y Y	2 - 3
LOCALE DATE	_	
LOCALE TIME	Y	1 - 2
LOCALE TIME FROM GEGOVER	Y	1 - 2
LOCALE-TIME-FROM-SECONDS	Y	1 - 2
LOG	Y	1

T 0 0 4 0		
LOG10	Y	1
LOWER-CASE	Y	1
LOWEST-ALGEBRAIC	Y	1
MAX	Y	Unlimited
MEAN	Y	Unlimited
MEDIAN	Y	Unlimited
MIDRANGE	Y	Unlimited
MIN	Y	Unlimited
MOD	Y	2
MODULE-CALLER-ID	Y	0
		-
MODULE-DATE	Υ	0
MODULE-FORMATTED-DATE	Y	0
MODULE-ID	Y	0
MODULE-PATH	Y	0
MODULE-SOURCE	Y	0
MODULE-TIME	Y	0
MONETARY-DECIMAL-POINT	Y	0
MONETARY-THOUSANDS-SEPARATOR	Y	0
NATIONAL-OF	N	1 - 2
NUMERIC-DECIMAL-POINT	Y	0
NUMERIC-THOUSANDS-SEPARATOR	Y	0
NUMVAL	Y	1
NUMVAL-C	Y	2
NUMVAL-F	Y	1
	Y	1
ORD MAY		_
ORD-MAX	Y	Unlimited
ORD-MIN	Υ	Unlimited
PI	Y	0
PRESENT-VALUE	Y	Unlimited
RANDOM	Y	Unlimited
RANGE	Y	Unlimited
REM	Y	2
REVERSE	Y	1
SECONDS-FROM-FORMATTED-TIME	Y	2
SECONDS-PAST-MIDNIGHT	Y	0
SIGN	Y	1
SIN	Y	1
SQRT	Y	1
STANDARD-COMPARE	N	2 - 4
STANDARD-DEVIATION	Y	Unlimited
STORED-CHAR-LENGTH	Y	1
SUBSTITUTE	Y	Unlimited
	=	
SUBSTITUTE-CASE	Y	Unlimited
SUM	Y	Unlimited
TAN	Y	1
TEST-DATE-YYYYMMDD	Y	1
TEST-DAY-YYYYDDD	Y	1
TEST-FORMATTED-DATETIME	Y	2
TEST-NUMVAL	Y	1
TEST-NUMVAL-C	Y	2
TEST-NUMVAL-F	Y	1
TRIM	Y	1 - 2

UPPER-CASE	Y	1
VARIANCE	Y	Unlimited
WHEN-COMPILED	Y	0
YEAR-TO-YYYY	Y	1 - 3

# Appendix D cobc --list-system

System routine	Parameters
SYSTEM	1
CBL_AND	3
CBL_CHANGE_DIR	1
CBL_CHECK_FILE_EXIST	2
CBL_CLOSE_FILE	1
CBL_COPY_FILE	2
CBL_CREATE_DIR	_ 1
CBL_CREATE_FILE	5
CBL_DELETE_DIR	1
CBL_DELETE_FILE	1
CBL_EQ	3
CBL_ERROR_PROC	2
CBL_EXIT_PROC	2
CBL_FLUSH_FILE	1
CBL_GET_CSR_POS	1
CBL_GET_CURRENT_DIR	3
CBL_GET_SCR_SIZE	2
CBL_IMP	3
CBL_NIMP	3
CBL_NOR	3
CBL_NOT	2
CBL_OC_GETOPT	6
CBL_OC_NANOSLEEP	1
CBL_OPEN_FILE	5
CBL_OR	3
CBL_READ_FILE	5
CBL_RENAME_FILE	2
CBL_TOLOWER	2
CBL_TOUPPER	2
CBL_WRITE_FILE	5
CBL_XOR	3
C\$CALLEDBY	1
C\$CHDIR	2
C\$COPY	3
C\$DELETE	2
C\$FILEINFO	2
C\$GETPID	0
C\$JUSTIFY	1
C\$MAKEDIR	1
C\$NARG	1
C\$PARAMSIZE	1
C\$PRINTABLE	1
C\$SLEEP	1
C\$TOLOWER	2
C\$TOUPPER	2
X"91"	2
X"E4"	0

X"E5"	0
X"F4"	2
X"F5"	2

## Appendix E cobc --list-mnemonics

Mnemonic names	
SYSIN	Device name
SYSIPT	Device name
STDIN	Device name
SYSOUT	${\tt Device\ name}$
SYSLIST	${\tt Device\ name}$
SYSLST	${\tt Device\ name}$
STDOUT	${\tt Device\ name}$
PRINTER	${\tt Device\ name}$
SYSERR	${\tt Device\ name}$
STDERR	Device name
CONSOLE	${\tt Device\ name}$
C01	Feature name
C02	Feature name
C03	Feature name
C04	Feature name
C05	Feature name
C06	Feature name
C07	Feature name
C08	Feature name
C09	Feature name
C10	Feature name
C11	Feature name
C12	Feature name
CSP	Feature name
FORMFEED	Feature name
CALL-CONVENTION	
SWITCH-0	Switch name
SWITCH-1	Switch name
SWITCH-2	Switch name
	DWICOH Hamo
SWITCH-3	Switch name
SWITCH-3 SWITCH-4	Switch name
SWITCH-4	Switch name
SWITCH-4 SWITCH-5	Switch name Switch name
SWITCH-4 SWITCH-5 SWITCH-6	Switch name Switch name Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7	Switch name Switch name Switch name Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8	Switch name Switch name Switch name Switch name Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8 SWITCH-9	Switch name Switch name Switch name Switch name Switch name Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8 SWITCH-9 SWITCH-10	Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8 SWITCH-9 SWITCH-10 SWITCH-11	Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8 SWITCH-9 SWITCH-10 SWITCH-11 SWITCH-12	Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8 SWITCH-9 SWITCH-10 SWITCH-11 SWITCH-12 SWITCH-13	Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8 SWITCH-9 SWITCH-10 SWITCH-11 SWITCH-12 SWITCH-13 SWITCH-14	Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8 SWITCH-9 SWITCH-10 SWITCH-11 SWITCH-11 SWITCH-12 SWITCH-13 SWITCH-14 SWITCH-15	Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8 SWITCH-9 SWITCH-10 SWITCH-11 SWITCH-12 SWITCH-13 SWITCH-14 SWITCH-15 SWITCH-16	Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8 SWITCH-9 SWITCH-10 SWITCH-11 SWITCH-12 SWITCH-13 SWITCH-14 SWITCH-15 SWITCH-16 SWITCH-17	Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8 SWITCH-9 SWITCH-10 SWITCH-11 SWITCH-12 SWITCH-13 SWITCH-14 SWITCH-15 SWITCH-16 SWITCH-17 SWITCH-17	Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8 SWITCH-9 SWITCH-10 SWITCH-11 SWITCH-12 SWITCH-13 SWITCH-14 SWITCH-15 SWITCH-16 SWITCH-17 SWITCH-17 SWITCH-18 SWITCH-19	Switch name
SWITCH-4 SWITCH-5 SWITCH-6 SWITCH-7 SWITCH-8 SWITCH-9 SWITCH-10 SWITCH-11 SWITCH-12 SWITCH-13 SWITCH-14 SWITCH-15 SWITCH-16 SWITCH-17 SWITCH-17	Switch name

SWITCH-22	Switch name
SWITCH-23	Switch name
SWITCH-24	Switch name
SWITCH-25	Switch name
SWITCH-26	Switch name
SWITCH-27	Switch name
SWITCH-28	Switch name
SWITCH-29	Switch name
SWITCH-30	Switch name
SWITCH-31	Switch name
SWITCH-32	Switch name
SWITCH-33	Switch name
SWITCH-34	Switch name
SWITCH-35	Switch name
SWITCH-36	Switch name
Extended mnemon	ic names (with -fsyntax-extension)
SWO	Switch name
SW1	Switch name
SW2	Switch name
SW3	Switch name
SW4	Switch name
SW5	Switch name
SW6	Switch name
SW7	Switch name
SW8	Switch name
SW9	Switch name
SW10	Switch name
SW11	Switch name
SW12	Switch name
SW13	Switch name
SW14	Switch name
SW15	Switch name
SWITCH 0	Switch name
SWITCH 1	Switch name
SWITCH 2	Switch name
SWITCH 3	Switch name
SWITCH 4	Switch name
SWITCH 5	Switch name
SWITCH 6	Switch name
SWITCH 7	Switch name
SWITCH 8	Switch name
SWITCH 9	Switch name
SWITCH 10	Switch name
SWITCH 11	Switch name
SWITCH 12	Switch name
SWITCH 13	Switch name
SWITCH 14	Switch name
SWITCH 15	Switch name
SWITCH 16	Switch name
SWITCH 17	Switch name
SWITCH 18	Switch name
~,,	

SWITCH	19	${\tt Switch}$	name
SWITCH	20	${\tt Switch}$	name
SWITCH	21	${\tt Switch}$	name
SWITCH	22	${\tt Switch}$	name
SWITCH	23	${\tt Switch}$	name
SWITCH	24	${\tt Switch}$	name
SWITCH	25	${\tt Switch}$	name
SWITCH	26	${\tt Switch}$	name
SWITCH	A	${\tt Switch}$	name
SWITCH	В	${\tt Switch}$	name
SWITCH	C	${\tt Switch}$	name
SWITCH	D	${\tt Switch}$	name
SWITCH	E	${\tt Switch}$	name
SWITCH	F	${\tt Switch}$	name
SWITCH	G	${\tt Switch}$	name
SWITCH	H	${\tt Switch}$	name
SWITCH	I	${\tt Switch}$	name
SWITCH	J	${\tt Switch}$	name
SWITCH	K	${\tt Switch}$	name
SWITCH	L	${\tt Switch}$	name
SWITCH	M	${\tt Switch}$	name
SWITCH	N	${\tt Switch}$	name
SWITCH	0	${\tt Switch}$	name
SWITCH	P	${\tt Switch}$	name
SWITCH	Q	${\tt Switch}$	name
SWITCH	R	${\tt Switch}$	name
SWITCH	S	${\tt Switch}$	name
SWITCH	T	${\tt Switch}$	name
SWITCH	U	${\tt Switch}$	name
SWITCH	V	${\tt Switch}$	name
SWITCH	W	${\tt Switch}$	name
SWITCH	X	${\tt Switch}$	name
SWITCH	Y	${\tt Switch}$	name
SWITCH	Z	${\tt Switch}$	name

## Appendix F Compiler Configuration

The following list was extracted from config/default.conf.

```
# Value: any string
name: "GnuCOBOL"
# Value: enum
standard-define
                                0
         CB\_STD\_OC = 0,
#
         CB_STD_MF,
#
         CB_STD_IBM,
#
         CB_STD_MVS,
#
         CB_STD_BS2000,
#
         CB_STD_ACU,
         CB_STD_85,
#
         CB_STD_2002,
         CB_STD_2014
# Value: int
tab-width:
                                8
text-column:
                                72
# Maximum word-length for COBOL words / Programmer defined words
# Be aware that GC checks the word length against COB_MAX_WORDLEN
# first (currently 61)
word-length:
                                31
# Value: 'mf', 'ibm'
assign-clause:
                                mf
# If yes, file names are resolved at run time using
# environment variables.
# For example, given ASSIGN TO "DATAFILE", the file name will be
# 1. the value of environment variable 'DD_DATAFILE' or
# 2. the value of environment variable 'dd_DATAFILE' or
# 3. the value of environment variable 'DATAFILE' or
# 4. the literal "DATAFILE"
# If no, the value of the assign clause is the file name.
filename-mapping:
                                yes
# Alternate formatting of numeric fields
pretty-display:
                                yes
# Allow complex OCCURS DEPENDING ON
complex-odo:
# Allow REDEFINES to other than last equal level number
indirect-redefines:
```

hostsign:

```
# Binary byte size - defines the allocated bytes according to PIC
# Value: signed unsigned bytes
               -----
              1 - 4
# '2-4-8'
                      same
               5 - 9 same
                                  4
             10 - 18 same
#
                                  8
#
# '1-2-4-8' 1 - 2 same
               3 - 4 same
5 - 9 same
                                  2
#
#
                                   4
             10 - 18 same
#
# '1--8'
              1 - 2
                      1 - 2
                                  1
               3 - 4
                        3 - 4
#
               5 - 6
                        5 - 7
#
                                   3
               7 - 9
#
                        8 - 9
                                   4
              10 - 11 10 - 12
              12 - 14 13 - 14
#
                                   6
#
              15 - 16 15 - 16
                                   7
              17 - 18 17 - 18
binary-size:
                             1-2-4-8
# Numeric truncation according to ANSI
binary-truncate:
                             yes
# Binary byte order
# Value: 'native', 'big-endian'
binary-byteorder:
                             big-endian
# Allow larger REDEFINES items
larger-redefines-ok:
                             no
# Allow certain syntax variations (eg. REDEFINES position)
relaxed-syntax-check:
                             no
# Perform type OSVS - If yes, the exit point of any currently
# executing perform is recognized if reached.
perform-osvs:
# If yes, linkage-section items remain allocated
# between invocations.
sticky-linkage:
# If yes, allow non-matching level numbers
relax-level-hierarchy:
# If yes, allow reserved words from the 85 standard
cobol85-reserved:
                             no
# Allow Hex 'F' for NUMERIC test of signed PACKED DECIMAL field
```

no

```
# If yes, set WITH UPDATE clause as default for ACCEPT dest-item,
# except if WITH NO UPDATE clause is used
accept-update:
                        no
# If yes, set WITH AUTO clause as default for ACCEPT dest-item,
# except if WITH TAB clause is used
accept-auto:
# not-reserved:
# Value: Word to be taken out of the reserved words list
# (case independent)
# Words that are in the (proposed) standard but may conflict
# Dialect features
# Value: 'ok', 'warning', 'archaic', 'obsolete', 'skip', 'ignore', 'error',
         'unconformable'
alter-statement:
                                        obsolete
author-paragraph:
                                        obsolete
data-records-clause:
                                        obsolete
debugging-line:
                                        ok
eject-statement:
                                        skip
entry-statement:
                                        obsolete
goto-statement-without-name:
                                        obsolete
label-records-clause:
                                        obsolete
memory-size-clause:
                                        obsolete
move-noninteger-to-alphanumeric:
                                        error
multiple-file-tape-clause:
                                        obsolete
next-sentence-phrase:
                                        archaic
odo-without-to:
                                        warning
padding-character-clause:
                                        obsolete
section-segments:
                                        ignore
stop-literal-statement:
                                        obsolete
synchronized-clause:
                                        ok
top-level-occurs-clause:
                                        ok
value-of-clause:
                                        obsolete
numeric-boolean:
                                        unconformable
acucobol-literals:
                                        unconformable
```

## Appendix G cobcrun --help

Usage: /d/Programme/Entwicklung/GnuCOBOL/gnu-cobol-2.0\_ultraclean2/bin/.libs/cobcrun [option or: /d/Programme/Entwicklung/GnuCOBOL/gnu-cobol-2.0\_ultraclean2/bin/.libs/cobcrun options

COBOL driver program for GnuCOBOL modules

#### Options:

-h, -help Display this help and exit

-V, -version Display cobcrun and runtime version and exit
-i, -info Display runtime information (build/environment)

-c <file>, -config=<file> Set runtime configuration from <file>
-r, -runtime-env Display current runtime configuration

This will show all settings and how they were set. Possible options are runtime configuration file,

environment (marked by 'env' when only set this way or

by 'Ovr' if this overrides the runtime setting) or default

### Appendix H Runtime configuration

The following list was extracted from config/runtime.cfg.

#### H.1 General instructions

The initial runtime.cfg file is found in the \$COB\_CONFIG\_DIR/config ( COB\_CONFIG\_DIR defaults to installdir/gnu-cobol ). The environment variable COB\_RUNTIME\_CONFIG may define a different runtime configuration file to read.

If settings are included in the runtime environment file multiple times then the last setting value is used, no warning occurs.

Settings via environment variables always take precedence over settings that are given in runtime configuration files. And the environment is checked after completing processing of the runtime configuration file(s)

All values set to string variables or environment variables are checked for **\$envvar** and replacement is done at the time of the setting.

Any environment variable may be set with the directive setenv . Example: setenv COB\_LIBARAY\_PATH \$LD\_LIBRARY\_PATH

Any environment variable may be unset with the directive unsetenv (one var per line). Example: unsetenv COB\_LIBRARY\_PATH

Runtime configuration files can include other files with the directive include. Example: include my-runtime-configuration-file

To include another configuration file only if it is present use the directive includeif. You can also use **\$envvar** inside this. Example: includeif \$HOME/mygc.cfg

If you want to reset a parameter to its default value use: reset parametername

Most runtime variables have boolean values, some are switches, some have string values, integer values and some are size values. The boolean values will be evaluated as following: to true: 1, Y, ON, YES, TRUE (no matter of case) to false: 0, N, OFF A 'size' value is an integer optionally followed by K, M, or G for kilo, mega or giga.

For convenience a parameter in the runtime.cfg file may be defined by using either the environment variable name or the parameter name. In most cases the environment variable name is the parameter name (in upper case) with the prefix  $\mathtt{COB}_-$ .

#### H.2 General environment

Environment name: COB\_DISABLE\_WARNINGS
Parameter name: disable\_warnings

Purpose: turn off runtime warning messages

Type: boolean Default: false

Example: DISABLE\_WARNINGS TRUE

Environment name: COB\_ENV\_MANGLE Parameter name: env\_mangle

Purpose: names checked in the environment would get non alphanumeric

change to '\_'

Type: boolean Default: false

Example: ENV\_MANGLE TRUE

Environment name: COB\_SET\_TRACE
Parameter name: set\_trace

Purpose: to enable to COBOL trace feature

Type: boolean Default: false

Example: SET\_TRACE TRUE

Environment name: COB\_TRACE\_FILE Parameter name: trace\_file

Purpose: to define where COBOL trace output should go

Type: string Default: stderr

Example: TRACE\_FILE \${HOME}/mytrace.log

#### H.3 Call environment

Environment name: COB\_LIBRARY\_PATH
Parameter name: library\_path

Purpose: paths for dynamically-loadable modules

Type: string

Note: the default paths .:/installpath/extras are always

added to the given paths

Example: LIBRARY\_PATH /opt/myapp/test:/opt/myapp/production

Environment name: COB\_PRE\_LOAD Parameter name: pre\_load

Purpose: modules that are loaded during startup, can be used

to CALL COBOL programs or  $\ensuremath{\text{C}}$  functions that are part

of a module library

Type: string

Note: the modules listed should NOT include extensions, the

runtime will use the right ones on the various platforms,

COB\_LIBRARY\_PATH is used to locate the modules

Example: PRE\_LOAD COBOL\_function\_library:external\_c\_library

Environment name: COB\_LOAD\_CASE
Parameter name: load\_case

Purpose: resolve ALL called program names to UPPER or LOWER case

Type: Only use UPPER or LOWER

Default: if not set program names in CALL are case sensitive

Example: LOAD\_CASE UPPER

Environment name: COB\_PHYSICAL\_CANCEL Parameter name: physical\_cancel

Purpose: physically unload a dynamically-loadable module on CANCEL,

this frees some  ${\tt RAM}$  and allows the change of modules during

run-time but needs more time to resolve CALLs (both to

active and not-active programs)

Alias: default\_cancel\_mode, LOGICAL\_CANCELS (0 = yes)

Type: boolean (evaluated for true only)

Default: false

Example: PHYSICAL\_CANCEL TRUE

#### H.4 File I/O

Environment name: COB\_VARSEQ\_FORMAT Parameter name: varseq\_format

Purpose: declare format to be used for variable length sequential

files (different types and lengths preceding each record)

Type: 0 means 2 byte record length (big-endian)

1 means 4 byte record length (big-endian)

2 means 4 byte record length (local machine int)
3 means 2 byte record length (local machine short)

Default: 0

Example: VARSEQ\_FORMAT 1

Environment name: COB\_FILE\_PATH Parameter name: file\_path

Purpose: define default location where data files are stored

Type: file path directory
Default: . (current directory)
Example: FILE\_PATH \${HOME}/mydata

Environment name: COB\_LS\_FIXED Parameter name: ls\_fixed

Purpose: Defines if LINE SEQUENTIAL files should be fixed length

(or variable, by removing trailing spaces)

Alias: STRIP\_TRAILING\_SPACES (0 = yes)

Type: boolean Default: false

Example: LS\_FIXED TRUE

Environment name: COB\_LS\_NULLS
Parameter name: ls\_nulls

Purpose: Defines for LINE SEQUENTIAL files what to do with data

which is not DISPLAY type. This could happen if a LINE

SEQUENTIAL record has COMP data fields in it.

Type: boolean Default: false

Note: The TRUE setting will handle files that contain COMP data

in a similar manner to the method used by Micro Focus COBOL

Example: LS\_NULL = TRUE

Environment name: COB\_SYNC Parameter name: sync

Purpose: Should the file be synced to disk after each write/update

Type: boolean
Default: false
Example: SYNC: TRUE

Environment name: COB\_SORT\_MEMORY Parameter name: sort\_memory

Purpose: Defines how much RAM to assign for sorting data

Type: size but must be more than 1M

Default: 128M

Example: SORT\_MEMORY 64M

Environment name: COB\_SORT\_CHUNK Parameter name: sort\_chunk

Purpose: Defines how much RAM to assign for sorting data in chunks

Type: size but must be within 128K and 16M

Default: 256K

Example: SORT\_CHUNK 1M

### H.5 Screen I/O

Environment name: COB\_BELL Parameter name: bell

Purpose: Defines how a request for the screen to beep is handled

Type: FLASH, SPEAKER, FALSE, BEEP

Default: BEEP

Example: BELL SPEAKER

Environment name: COB\_REDIRECT\_DISPLAY Parameter name: redirect\_display

Purpose: Defines if DISPLAY output should be sent to 'stderr'

Type: boolean Default: false

Example: redirect\_display Yes

Environment name: COB\_SCREEN\_ESC Parameter name: screen\_esc

Purpose: Enable handling of ESC key during ACCEPT

Type: boolean Default: false

Note: is only evaluated if COB\_SCREEN\_EXCEPTIONS is active

Example: screen\_esc Yes

Environment name: COB\_SCREEN\_EXCEPTIONS
Parameter name: screen\_exceptions

Purpose: enable exceptions for function keys during ACCEPT

Type: boolean Default: false

Example: screen\_exceptions Yes

Environment name: COB\_TIMEOUT\_SCALE
 Parameter name: timeout\_scale

Purpose: specify translation in milliseconds for ACCEPT clauses

BEFORE TIME value / AFTER TIMEOUT

Type: integer

0 means 1000 (Micro Focus COBOL compatible), 1 means 100

(ACUCOBOL compatible), 2 means 10, 3 means 1

Default: (

Example: timeout\_scale 3

Environment name: COB\_INSERT\_MODE Parameter name: insert\_mode

Purpose: specify default insert mode for ACCEPT; 0=off, 1=on

Default: false

Example: insert\_mode Y

Environment name: COB\_LEGACY Parameter name: legacy

Purpose: keep behaviour of former runtime versions, currently only

for setting screen attributes for non input fields

Type: boolean
Default: not set
Example: legacy true

Note: If you want to slightly speed up a program's startup time, remove all of the comments from the actual real file that is processed

## $\mathbf{Index}$

$\mathbf{A}$	Extensions not ISO/ANSI standard 15
ACCEPT special keys       16         Arrow keys       16         AUTO       15         AUTO-SKIP       15	<b>H</b> Home keys
В	I
Backspace key       16         BELL       17         BLANK LINE       17         BLANK SCREEN       17	Indexed         15           Indexed file packages         15           Insert key         16
D	P
Delete keys	PROTECTED 15
	$\mathbf{S}$
E	SELECT
End keys       16         ERASE EOL       17         ERASE EOS       17	SELECT ASSIGN TO       15         SIZE       15, 17
Extended ACCEPT statement	${f T}$
Extensions	Tab keys