# GUI\_UserInterface - Main Menu

# **Revision history**

2017-04-10	Don Ferguson	Original draft
2018-05-26	Rod Thompson	Add diagrams, actions, maps
2018-06-12	Rod Thompson	Replace main window graphic
		Update REQUIRED SERVICES – Dependencies
		Replace BR_PanelConfig with BR_WindowConfig
2018-06-16 Rod Thompson		Add IMPORT and EXPORT to Tools Menu
		Move Import from TMG from Project menu to Tools>Import
		Replace relevant graphics & Windows Interaction Maps
2018-06-23	Rod Thompson	Revise startup 'Splash screen' information
	·	Add graphic
		Add main window- top-left-corner image (application icon)
		Replace main window graphic
		Add Tools>Admin>Update Schema (from BR 07.25)
		Replace Tools menu graphic
2018-06-26	Rod Thompson	Add 'Exit' to main menu (LOOK AND FEEL)
		Replace main window graphic
		Replace Windows Interaction Map (main)
		Add Process Flow Chart
		Add OPERATION
		Add Note to SCOPE
		Addition to icon actions – 'X'close
		Add Project Close to REQUIRED SERVICES - Dependencies
2018-06-29	Don Ferguson	Add ProjectAdmin into Look and Feel list
2018-06-30	Rod Thompson	Edit Tools>Admin
2010 00 30	Rod Monipson	Delete extra Startup splash screen
2018-07-07	Rod Thompson	Delete 'Recent' from Project Menu
2018-10-10	Rod Thompson	Replace Graphics (configuration change)
2016-10-10	Rou mompson	Add window location detail
		Add Viewpoint to Tools>Settings menu
		Amend REQUIRED SERVICES – Dependencies
		Add Window Size/Location change to EVENT ACTIONS
		Add Logging to Reports Menu
		Amend DATA CONTROLLED
		Replace Process Flow Chart
2018-11-17	Rod Thompson	Add User Rights to Tools>Admin Menu
2010-11-17	Kou mompson	Add list of Enabled menus at Startup/Close
2010 11 22	Dod Thereses	
2018-11-23	Rod Thompson	Replace Process Flow Chart
		Add detail for Splash Screen
		Revise ACTIONS and EVENT ACTIONS
2040 42 45	5 5	Revise REQUIRED SERVICES
2018-12-15	Don Ferguson	Revise Menu Item list in Look and Feel
2019-01-29	Rod Thompson	LOOK AND FEEL - Remove 'Exit' from Main menu
		ENABLED – Startup – remove Exit
		EVENT ACTIONS – icon actions – Amend X close action
		Amend Main Display graphic (rename as Main Window)
		Replace Window Interaction Map (first graphic)
		Amend ACTION, item 8
2019-01-30	Rod Thompson	Add new menu functions
		Project compare
		Project split
		Project merge
		Replace graphic & Windows Interaction Map

	<del>-</del>		
	Update REQUIRED SERVICES - Dependencies		
	Remove 'Client' from Tools>Settings menu		
	Revise Process Flowchart		
Rod Thompson	Replace graphic-Splash screen		
	Update Window Interactions Maps		
Don Ferguson/RT	Add Viewpoints to main menu		
	Replace graphics (V12)		
	Update WINDOW INTERACTION MAP (v7)		
Rod Thompson	Revise ExitHRE operation		
	Remove GUI_ExitHRE module		
	Replace WINDOW INTERACTION MAP-Project (v8)		
	ACTIONS – Add Note to Exit item		
	Add USE CASES		
	Replace Process flowchart(v13)		
Don Ferguson	Show real screen images as mockups		
Rod Thompson	Add Server Logoff		
'	Replace process flowchart(v14)		
	Amend ACTIONS - Exit		
Rod Thompson	Amend ENABLED MENUS at STARTUP and CLOSE		
'	Add Reports		
	Don Ferguson/RT  Rod Thompson  Don Ferguson  Rod Thompson		

#### **SCOPE**

This is the HRE program executable, which controls, via user action, all other HRE functions.

Note: Additional controls on accessibility are likely when access rights control is implemented.

## **LOOK AND FEEL**

The initial window should be centred within the user's main screen, showing the HRE main menu at the top, and optionally display the HRE splash screen (logo, version, disclaimers, etc) which is also part of this module.

The main menu and sub-menu items are (currently committed for HRE versions 0.1 - 0.3 ONLY):

Project

0	Open Project	invokes	GUI_OpenProject
0	New Project	"	GUI_ProjectNew
0	Backup Project	"	GUI_ProjectBackup
0	Restore Project	"	GUI_ProjectRestore
0	Close Project	"	GUI_ProjectClose
0	Compare Projects	"	GUI_ProjectCompare
0	Merge Projects	"	GUI_ProjectMerge
0	Split Projects	"	GUI_ProjectSplit
0	Copy Project As	"	GUI_ProjectCopyAs
0	Rename Project	"	GUI_ProjectRename
0	Delete Project	"	GUI_ProjectDelete
0	Exit HRE		
erson			(functionality added in v0.2)
0	Select By ID, etc	invokes	GUI_EntitySelect
0	Recently Used	"	GUI_RecentVisit
0	Manage Persons		
	<ul><li>Add</li></ul>	"	GUI_EntityEdit
	<ul><li>Delete</li></ul>	u	GUI_EntityDelete
	<ul><li>Edit</li></ul>	"	GUI_EntityEdit

Manage Person Name Styles Add GUI NameStyleEdit Delete GUI NameStyleDelete " Edit GUI\_NameStyleEdit Manage Person Flags " GUI EntityEdit Add " Delete GUI\_EntityDelete Edit GUI EntityEdit Manage Person Notepads Add GUI EntityEdit " GUI EntityDelete Delete Edit GUI EntityEdit Manage Person Accents Select GUI\_AccentSelect Link to Flag GUI AccentLink Delete GUI AccentDelete Edit GUI AccentEdit **Associates** (functionality added in v0.3) Manage Event Associates Manage Event Associate Flags Manage Event Associate Notepads Manage Task Associates Manage Task Associate Flags Manage Task Associate Notepads Research Types (functionality added later) Viewpoints Open Person Viewpoint **GUI** Viewpoint Open Event Viewpoint **GUI** Viewpoint **Open Location Viewpoint GUI** Viewpoint Events/Tasks (functionality added in v0.3) Events Select By ... Pick List Manage Events ... Manage Event Flags ... Manage Event Notepads ... Tasks (functionality added in v0.3) Select By ... Pick List Manage Tasks ... Where/When Location Select By ID, etc invokes GUI\_EntitySelect **Recently Used** GUI\_RecentVisit Manage Locations " GUI\_EntityEdit Add GUI EntityDelete Delete Edit GUI EntityEdit Manage Location Name Styles Add GUI\_NameStyleEdit Delete GUI\_NameStyleDelete

```
(functionality added in v0.3)
       Occasions
                Select By...
                Recently Used
                Manage Occasions...
       Historical Dates
                                (needs further input once GUI HistoricalDates developed)
                                        invokes GUI EntitySelect
                Select By Date, etc
                Recently Used
                                                GUI RecentVisit
                Manage Historical Dates ...
                Date Converter
                                        (functionality added in v0.3)
                                        (functionality added in v0.3)
                Date Calculator
Evidence
                                        (functionality added in v0.4)
       Sources
    0
       Citations
                                        (functionality added in v0.4)
    0
                                        (functionality added in v0.4)
        Repositories
    0
       Images
                                        (functionality added in v0.4)
    0
                                        (functionality added in v0.4)
       External Files
    0
       Internal Text
                                        (functionality added in v0.4)
    0
                                        functionality added in v0.6+)
Reports (
        List of...
    0
                                        invokes GUI_Logging
    0
        Logging
Tools
       Settings
    0
                User
                                invokes GUI AppSetting
                Server
                                        ditto
                                        ditto
                Monitor
                GUI Language
                                        ditto
                                invokes GUI ProjectSetting (added in v0.2)
                Persons
                                invokes GUI_ProjectSetting
                Project
                Locations
                                        ditto
                Events
                                        (added in v0.3)
                Tasks
                                        (added in v0.3)
                Occasions
                                        (added in v0.3)
                Historical Dates invokes GUI ProjectSetting
                Sources
                                        (added in v0.4)
                Source Name Styles
                                        (added in v0.4)
                Repositories
                                        (added in v0.4)
                Repository-Source links (added in v0.4)
        Application Language
                                invokes GUI_AppLanguageSelect
                Select
                                  "
                Delete
                                        GUI_AppLanguageDelete
                                        GUI AppLanguageEdit
                Edit
        User Language
                Select
                                invokes GUI UserLanguageSelect
                                        GUI UserLanguageDelete
                Delete
                                   "
                Edit
                                        GUI_UserLanguageEdit
       Import...
                From TMG
                                ...."
                                        GUI ProjectImportTMG (part added in v0.1)
        Export...
    0
       Administration...
                Edit AUX files
                                invokes GUI_ProjectAdmin
```

GUI NameStyleEdit

Edit

Update Schema (added in v0.4)

Edit User Rights

Help

Search Help invokes GUI\_Help

HRE website (connects to www.historyresearchenvironment.org)

About HRE invokes GUI HelpAbout

Further additions to the sub-menus will be defined in later HRE documentation updates.

#### **OPERATION**

When each user of HRE opens HRE for the first time, no history of use will exist.

Accordingly, a limited number of selections from the main menu will be available. See below. After the first-time use, in which a project is opened or created by the user; on each subsequent occasions of use of HRE, the user will have access to all menu selections (subject to User Rights).

#### **MOCKUP WINDOWS**

#### Splash Screen

Used during the software startup phase, displayed for a period of time (to be determined) providing a visual response to the User of the starting process.



The Splash Screen window is hard-coded.


Location: Centred on main screen of User's computer.

Use or otherwise of the Splash Screen during startup is a User Option.

This is an entry in the App Settings module, which once set is copied to the UserAUX file, from whence the option is then used in subsequent starts of HRE. Note – this setting will apply to all projects accessed by the User.

NB: display of this window must be started on its own dispatching thread, otherwise the delay in its closing will simply delay the opening processes of the program.

#### Main Window/Startup Display



The Main Window is hard-coded, Location and Size variable.

Startup Location: Centred on main screen of User's computer.

Working location and size determined in Project creation, recalled on subsequent Project Opens.

Menu sub-windows:				
Open Project				
New Project				
Backup Project				
Restore Project				
Close Project	Select by ID			
Compare Projects	Recently Used			
Merge Projects	Manage Persons			
Split Projects	Manage Name Styles			
Copy Project As	Manage Person Flags			
Rename Project	Manage Person Notepads			
Delete Project	Manage Person Accents Open Genealogical Viewpoint			
Exit HRE	Associates Open Genealogical Viewpoint			
Sources Citations Repositories Images Images External Files Occasions Internal Text Logging				
Settings Application Language User Language Import Export Administration	Search Help HRE website About HRE			

Note: In the above illustrations of the menu pulldowns, the blue square indicates only the possible location of an icon. This space will otherwise be blank.

Location (for each Menu sub-window) is as a footer to the relevant Menu button.

# **ENABLED MENUS at STARTUP and CLOSE**

Main menu	Sub-menu	
Project	Open, New, Restore	
Reports	Logging	
Tools	Settings & Admin (some selections)	
Help	Search Help, HRE website, AboutHRE	

Other selections are disabled. Menu buttons are visible but greyed.

# **DEFINITIONS**

#### Display Area

The area of the computer display which is used by HRE. Location and size may be changed by the User.

#### **ACTIONS**

The fundamental operations are:

- 1) Open the program
- 2) Display the Splash screen
- 3) Search for the UserAUX file -if existing, read the file
- 4) Add the HRE Startup Display
  Hereafter referred to as the Main Display window.
- 5) Add a border component (boundary of the HRE Startup Display) non-visible This becomes the HRE Display Area
- 6) Accept user action to change the location and size of the Main Display window (with consequential change to the HRE Display Area) The changes are saved to the configurations in the Project database
- 7) Action user menu selections as per the 'Look and Feel' section above
- 8) Exit the program (using Exit function close Server connections as required).

#### **USED BY**

All HRE users.

#### **DATA CONTROLLED BY THIS MODULE**

1. Main display Window settings.

#### **REQUIRED DATA CONTROLLED BY OTHER MODULES**

1. None.

## **REQUIRED SERVICES - Dependencies**

GUI modules as defined in 'Look and Feel' section above.

The table below is a small sample only.

Dependency information contained in the relevant module specifications.

First-Order Dependencies	Second-Order Dependencies	Higher-Order Dependencies
07.17 BR_WindowConfig	07.06 BR_GuiElement	
	07.02 BR_EntityLink	
	07.29 BR_Translation	
	07.16 BR_MessagePatterns	
04.07 GUI_ProjectClose	04.05 GUI_ProjectBackup	
	04.14 GUI_ProjectSummary	
	04.13 GUI_ExitHRE	
	07.17 BR_WindowlConfig	
	07.21 BR_Project	
07.30 BR_Viewpoint	07.06 BR_GuiElement	
	07.17 BR_WindowlConfig	
	07.02 BR_EntityLink	
	07.29 BR_Translation	
	07.03 BR_FieldDefinition	
07.21 BR_Project	07.06 BR_GuiElement	
	07.02 BR_EntityLink	
	07.29 BR_Translation	
	07.03 BR_FieldDefinition	

#### LOGGING

General use of the HRE Main display will not create log entries. Setting changes to this Window (location and size) will create log entries.

#### **EVENT ACTIONS**

Keyboard actions
 Not applicable

#### 2) Mouse actions

Drag and drop mouse actions to move and resize windows Setting changes saved to database for User>Project>Viewpoint>Window. Left key

- a. Mouse key click on main Menu labels, opens a pulldown window for the selected menu, and allows further selection of the sub-menu items using an icon or name
- b. Mouse key click on icons (detailed below).

#### Right key

#### To be determined

- 3) Icon actions
  - a. left mouse key click on icons in the Window Control group:
    - a. 'X' icon

(closes the window)

NOTE: If there is an open project – uses the Close & Exit functions

b. 'Box' icon

Toggles the window size between full screen, and the preset window size

c. 'Dash' icon

Minimizes the window, to an icon on the screen toolbar.

A click on the toolbar icon restores the display to its previous setting

4) Keyboard shortcuts

To be determined

The HRE Main display is generally the only window which can be 'maximized' or minimized. When 'Maximized', the Main Display window fills the screen on which it was displayed, with no other changes to the Main Display window content or to other HRE Viewpoints and Windows. The Maximize icon changes to one displaying two squares, one atop the other.

When 'Minimized', the Main Display window closes, along with all other Viewpoints for the Project; with the taskbar icon for HRE remaining. Clicking on the taskbar icon reopens the HRE displays.


#### WARNING CONDITIONS


 Need details of the condition that raised the warning, example message and possible next steps.


## **ERROR CONDITIONS**


1. Need to record the condition that raised the error, example message and possible next steps.


#### WINDOW INTERACTION MAPS























#### **USE CASES**

1) ExitHRE

Use Case 1
ExitHRE

Use of the 'Close and Exit HRE' selection on the Project menu does not invoke a separate GUI module.

Action taken is determined by the number of projects that are open in HRE.

- Where there are NIL projects open, the shutdown code is executed
- Where this is ONE project open, that project is 'closed' (with prior backup determined by the appropriate setting in 05.01 GUI\_AppSetting module), then the shutdown code is executed
- Where MORE THAN ONE project is open, the 04.07 GUI ProjectClose module is involved.

