$\begin{array}{c} \mathbf{MPINT-Documentation} \\ \mathbf{Version} \ 1.0 \end{array}$

Author:

Grégory Essertel

3rd December 2015

Contents

1	Introduction			
2	Background			
3	Setup			
4	Data Structure			
5	Utils 5.1 new_mpint 5.2 delete_mpint 5.2 delete_mpint 5.3 init_mpint 5.4 clear_mpint 5.5 extend_mpint 5.5 extend_mpint 5.6 write_bigendian_mpint 5.7 hton_mpint 5.8 read_bigendian_mpint 5.9 ntoh_mpint 5.10 copy_mpint 5.11 subval_mpint 5.12 subvalghost_mpint 5.12 subvalghost_mpint 5.14 swap_mpint 5.15 parse_mpint 5.15 parse_mpint 5.16 print_mpint 5.16 print_mpint	2 2 2 2 2 2 3 3 3 3 4 4 4 4 4 4 5		
6	Comparaison 6.1 cmp_mpint 6.2 unsigncmp_mpint	5 5		
7	Summation 7.1 add_mpint / sub_mpint . . 7.2 low order functions . . 7.2.1 addcst_mpint . . 7.2.2 unsignadd_mpint . . 7.2.3 diff_mpint . .	5 5 6 6		
	Product 8.1 mul_mpint	6 6 7 7 7 7		
10	Exponentiation 10.1 MPPRIME 10.1.1 Data structure 10.1.2 init_mprime 10.1.3 clear_mprime 10.1.4 precompprime_mpint 10.2 Montgomery operations 10.2.1 montgomery_mpint 10.2.2 montgomery_inv_mpint 10.2.3 Macros	8 8 8 8 8 8 8 9 9 9		
	10.3 powmod_mpint	9		

	10.6	Exampel $2 \dots $	10
11	bits	operations rshift_mpint	11
	11.2	rshiftw_mpint	11
	11.3	lshift_mpint	11
	11.4	$safelshift_mpint \dots \dots$	12
	Ran		12
	12.1	rand_mpint	12
	12.2	$rand mod_mpint \dots \dots$	13
13	Perf	formance evaluation	13

1 Introduction

MPINT is a multi-precision integer library supported for the Xinu operating system. Tested so far only for the Galileo version.

This library provides the basic arithmetic operation such as addition, subtraction, multiplication, division etc. The initial design is not efficiency, some efficiency tests have been perform and can be seen at the Section 13.

2 Background

The reader is expecting to have a knowledge about Xinu, more precisely the low level memory management with getmem and freemem. Also the constant SYSERR is used in this document.

3 Setup

Some constants have to be set in the mpint.h file.

The operations require to define an HALF_WORD. The HALF_WORD should be half of the size of the registers, this trick is used to handle carries easily. On the Galileo board for example we define:

```
typedef uint16 HALF_WORD;
typedef uint32 WORD;
typedef int32 SWORD;
```

Some other constant are used for the computation:

```
#define HW_BITS (16) // 8 * sizeof(HALF_WORD)
#define HW_MASK (0xFFFF) // 1 << HW_BITS - 1
```

NOTE: the HALF_WORD and WORD have to be unsigned.

4 Data Structure

```
typedef struct mpint {
   HALF_WORD* val;
   uint32   size;
   uint32   order;
   int32   sign;
} MPINT;
```

Code 1: MPINT structure

The basic structure used in the complete project is the MPINT. The structure stores a pointer to an array of $HALF_WORD$ as well as the size of the corresponding allocated memory. The little endian convention is used here, meaning that the value of a number of two $HALF_WORD$ is " $val[1] << HW_BITS + val[0]$ ". The size of the array has to be a multiple of the variable $MPINT_HWINIT$ plus one $HALF_WORD$. When more space is required, the size is increase by $MPINT_HWINIT$.

```
#define MPINT_INIT 1024
#define MPINT_HWINIT 64 // MPINT_INIT / (8 * sizeof(HALF_WORD))
```

With these values, the smaller MPINT is a 1024 bits integer and 2048, 3062... are possible values.

The order of a number is defined as the index of the Most Significant Halfword +1. Therefore a number is equal to zero if and only if the order is equal to 0.

The sign is either +1 or -1. When constructed 0 has the sign +1, but there is no grantees on the sign of 0 if it is the output of an operation.

5 Utils

The library offers some utility function in order to manipulate the MPINT.

5.1 new_mpint

Prototype

```
MPINT* new_mpint();
```

Description Allocate and initialize a new MPINT on the heap.

Error Return SYSERR if an error occurs (Out Of Memory)

5.2 delete_mpint

Prototype

```
void delete_mpint(MPINT*);
```

Description Release memory used by an MPINT previously allocated on the heap using new_mpint .

5.3 init_mpint

Prototype

```
void init_mpint(MPINT*);
```

Description Initialize a MPINT.

Note Initializing an already initialized MPINT can lead to memory leak.

5.4 clear_mpint

Prototype

```
void clear_mpint(MPINT*);
```

Description Releases the memory used by a MPINT, but not the memory used by the structure MPINT. **Note** Generally used for a MPINT declared on the stack.

5.5 extend_mpint

Prototype

```
bool8 extend_mpint(MPINT* n, int32 new_size);
```

Description Extends the size of n to be at least new_size .

Note This function is destined to be used by developers, a user should not have to ue it.

Return the function returns TRUE if it has been successful, FALSE otherwise.

5.6 write_bigendian_mpint

Prototype

```
void write_bigendian_mpint(byte* buff, MPINT* src, int32 len);
```

Description Write the *len* less significant bytes of *src* into the buffer *buff*

5.7 hton_mpint

Prototype

```
int32 hton_mpint(byte* buff, MPINT* src, int32 len);
```

Description Formats *src* into a machine independant representation using maximum *len* bytes. The format is: —length (4 bytes)—sign (0 or 1 byte)—value using big endian representation.

Return The function returns the number of bytes used or SYSERR if an error occured. (Buffer to small).

5.8 read_bigendian_mpint

Prototype

```
bool8 read_bigendian_mpint(MPINT* dst, byte* buff, int32 length);
```

Description Sets the value of the *dst MPINT* to the value in the buffer using the *length* first byte in a big endian order.

Return The function returns TRUE if it has been successful, FALSE otherwise.

5.9 ntoh_mpint

Prototype

```
bool8 ntoh_mpint(MPINT* dst, byte* buff);
```

Description Reads a MPINT formated with the $hton_mpint$ function.

Return The function returns the number of bytes read and SYSERR if an error occured.

5.10 copy_mpint

Prototype

```
bool8 copy_mpint(MPINT* dst, MPINT* src);
```

Description Sets the value of *dst* to the value of *src*.

Return The function returns TRUE if it has been successful, FALSE otherwise.

5.11 subval_mpint

Prototype

```
bool8 subval_mpint(MPINT* dst, int32 offset, MPINT* src, int32 start,
int32 length);
```

Description Sets the value of dst between the $HALF_WORD$ offset and offset + length - 1 to the value of src between the $HALF_WORD$ start and start + length - 1.

Return The function returns TRUE if it has been successful, FALSE otherwise.

5.12 subvalghost_mpint

Prototype

```
bool8 subvalghost_mpint(MPINT* dst, MPINT* src, int32 start, int32 length);
```

Description Sets the value of dst to the value of src between the $HALF_WORD$ start and start + length - 1.

Note WARNING: This function does not copy the value, therefore it should only be used in a read only mode.

Return The function returns TRUE if it has been successful, FALSE otherwise.

5.13 uporder_mpint

Prototype

```
bool8 uporder_mpint(MPINT* n);
```

Description Updates the order of the MPINT

Note This function is for developer only, user should not have to us it.

Return The function returns FALSE if the order is greater than the size of the MPINT.

5.14 swap_mpint

Prototype

```
void swap_mpint(MPINT* v1, MPINT* v2);
```

Description Swaps two MPINT.

5.15 parse_mpint

Prototype

```
bool8 parse_mpint(MPINT* n, char* val, int32 length);
```

Description Parses an *MPINT* from the *length* first character of the string *val* (lower and upper case for a,b,c,d, e and f are accepted). Negative value can be parsed as well.

Note If a non hexadecimal digit is found in the string of character, the behavior is undefined (other than the '-' at the beginning).

Return The function returns TRUE if it has been successful, FALSE otherwise.

5.16 print_mpint

Prototype

```
void print_mpint(MPINT* n);
```

Description Prints a *MPINT* in its hexadecimal representation.

6 Comparaison

6.1 cmp_mpint

Prototype

```
int32 cmp_mpint(MPINT* v1, MPINT* v2);
```

Description Compares two MPINT.

Return 1 if v1 > v2, 0 if v1 = v2 and -1 if v1 < v2

6.2 unsigncmp_mpint

Prototype

```
int32 unsigncmp_mpint(MPINT* v1, MPINT* v2);
```

Description Compares the absolute value of two MPINT.

Return 1 if |v1| > |v2|, 0 if |v1| = |v2| and -1 if |v1| < |v2|

7 Summation

7.1 add_mpint / sub_mpint

Prototype

```
bool8 add_mpint(MPINT* v1, MPINT* v2);
bool8 sub_mpint(MPINT* v1, MPINT* v2);
```

Description Computes the operation v1 + / - v2 and stores the result in v1.

Return The function returns TRUE if it has been successful, FALSE otherwise.

7.2 low order functions

The lower order function aim to provide programmers with more efficient routines. However they are more difficult to use and can lead to unexpected bugs.

7.2.1 addcst_mpint

Prototype

```
bool8 addcst_mpint(MPINT* v, HALF_WORD d, int32 index);
```

Description Computes $v + d \times 2^{index \times HW_BITS}$ and stores the result in v.

Note This function does not extends the MPINT if necessary. The result is truncated to the size of the original MPINT.

Return The function returns TRUE if it has been successful, DIRTY if the result has been truncated and FALSE if an error occurred.

7.2.2 unsignadd_mpint

Prototype

```
bool8 unsignadd_mpint(MPINT* v1, MPINT* v2);
```

Description Computes |v1| + |v2| and stores the result in v1.

Note The sign of v1 is undefined afterward.

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

7.2.3 diff_mpint

Prototype

```
bool8 diff_mpint(MPINT* v1, MPINT* v2, int32 biggest);
```

Description Computes |v1-v2| and stores the result in v1. If the value of biggest is 1, it indicates that the absolute value of v1 id grater than the one of v2, -1 is the opposite and 0 means that the user doesn't know.

Note The sign of v1 is undefined afterward.

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

8 Product

8.1 mul_mpint

Prototype

```
bool8 mul_mpint(MPINT* dst, MPINT* v1, MPINT* v2, bool8 trunc);
```

Description Computes the operation $dst + v1 \times v2$ and stores the result in dst. If trunc is TRUE, the size of dst is extend to v1 size and the result is then truncated.

Note

- If dst is not empty and its size bigger than v1, the result with trunc set to TRUE will be undefined. (The carry won't be propagated further than v1 size).
- If dst is not empty and $sizeof(dst + v1 \times v2) > sizeof(v1) + sizeof(v2)$, then the extra $HALF_WORD$ will be used and the DIRTY value will be returned. The user has to ensure that this state is temporary.

Example: $9999 + 99 \times 99 = 19800$, the number requires 5 digits but has been prepared for only 4.

Return The function returns TRUE if it has been successful, DIRTY (cf. NOTE) and FALSE otherwise.

8.2 square_mpint

Prototype

```
bool8 square_mpint(MPINT* dst, MPINT* v);
```

Description Computes v^2 and store the result in dst.

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

8.3 mulcst_mpint

Prototype

```
bool8 mulcst_mpint(MPINT* v1, HALF_WORD n);
```

Description Computes $v1 \times n$ in place.

Note v1 is not extended, the DIRTY value is returned if the extra $HALF_WORD$ is used. The user has to ensure that this state is temporary.

Example: $99 \times 9 = 891$. 3 digits are used but the original size of v1 was 2.

Return The function returns TRUE if it has been successful, DIRTY (cf. NOTE) and FALSE if an error occurred.

9 Division

9.1 unsigndiv_mpint / unsignmod_mpint

Prototype

```
bool8 unsigndiv_mpint(MPINT* a, MPINT* b, MPINT* q, MPINT* r);
bool8 unsignmod_mpint(MPINT* r, MPINT* a, MPINT* b);
```

Description Computes $\lfloor \lfloor \frac{a}{b} \rfloor \rfloor$ in q and $a \mod b$ in r.

Note Theses functions are using two auxiliary functions called recursively.

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

9.2 invmod_mpint

Prototype

```
bool8 invmod_mpint(MPINT* x, MPINT* p);
```

Description Computes y such that $x \times y = 1 \mod p$ and put the result in x.

Note If such a value doesn't exist the function simply returns FALSE.

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

10 Exponentiation

Currently, this library only support modular exponentiation with the modulus being an ODD number. This is due to the fact that the implementation uses the Montgomery transformation: Wikipedia page.

10.1 MPPRIME

10.1.1 Data structure

Like the MPINT, each MPPRIME is considered to be a 1024 bits prime or 2048 bits.... Therefore we define R to be the upper bound of the MPINT with the particular size. For example, if a number is a 1024 bits integer, then the corresponding R is 2^{1024} .

```
typedef struct prime {
   MPINT num;
   MPINT inv;
   MPINT r_square;
} MPPRIME;
```

Code 2: MPPRIME structure

- num is the value of the prime number.
- inv is the number such that $num \times inv \mod R = -1$, with R defined as above.
- r-square is the number $R^2 \mod num$, with R defined as above.

NOTE: this data structure could be used with any odd integer.

10.1.2 init_mprime

Prototype

```
void init_mpprime(MPPRIME* mp);
```

Description Initialize a MPPRIME.

10.1.3 clear_mprime

Prototype

```
void clear_mpprime(MPPRIME* mp);
```

Description Releases the memory used by a MPPRIME, but not the memory used by the structure MPPRIME.

10.1.4 precompprime_mpint

Prototype

```
bool8 precompprime_mpint(MPPRIME* prime);
```

Description Computes y such that $x \times y = 1 \mod p$ and put the result in x.

Note If such a value doesn't exist the function simply returns FALSE.

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

10.2 Montgomery operations

We first define some routines that we describe here. A user should use the macro defined in the next section 10.2.3.

10.2.1 montgomery_mpint

Prototype

```
bool8 montgomery_mpint(MPINT *v1, MPINT *v2, MPINT* n, MPINT* inv_n);
bool8 montgomery_square_mpint(MPINT *v, MPINT* n, MPINT* inv_n);
```

Description Computes the Montgomery reduction of v1 by v2 modulo n and puts the result in v1.

Note The value v1 and v2 are the representation of some numbers in the Montgomery space (cf Examples 10.5).

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

10.2.2 montgomery_inv_mpint

Prototype

```
bool8 montgomery_inv_mpint(MPINT *v1, MPINT* n, MPINT* inv_n);
```

Description Computes the real value of the value v1 from the Montgomery space modulo n and puts the result in v1.

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

10.2.3 Macros

```
#define montgomery_mul_mpint(v1, v2, p) \
montgomery_mpint(v1, v2, &((p)->num), &((p)->inv))

#define montgomery_square_mpint(v1, p) \
montgomery_square_mpint(v1, &((p)->num), &((p)->inv))

#define to_montgomery_mpint(v1, p) \
montgomery_mpint(v1, &((p)->r_square), &((p)->num), &((p)->inv))

#define from_montgomery_mpint(v1, p) \
montgomery_inv_mpint(v1, &((p)->num), &((p)->fginv))
```

10.3 powmod_mpint

Prototype

```
#define REAL     0
#define MONTGOMERY 1
bool8 powmod_mpint(MPINT *b, MPINT *n, MPPRIME *N, int32 output_space);
```

Description Computes the value $b^n \mod N$ and store it in b. If $output_space$ is equal to MONTGOMERY, the result is stored in its Montgomery form. Otherwise it is in its real form.

Note Having the result in its Montomery form can be useful for computing $(a \times b^c) \mod N$. See Example 10.6

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

10.4 Examples

10.5 Exampel 1

Compute 34×43 mod 97. (This is not efficient for only one operation, it is better to use mul_mpint and unsignmod_mpint).

```
MPPRIME p97;
 MPINT i34, i43;
5 init_mpint(&i34);
6 init_mpint(&i43);
init_mpprime(&p97);
 word_mpint(&i34, 34, 1);
10
word_mpint(&i43, 43, 1);
word_mpint(&(p97.num), 97, 1);
precompprime_mpint(&p97);
 to_montgomery_mpint(&i34, &p97);
 to_montgomery_mpint(&i43, &p97);
17
19
montgomery_mul_mpint(&i34, &i43, &p97);
 // Back to real value
from_montgomery_mpint(&i34, &p97);
print_mpint(&i34);
27
clear_mpint(&i34);
30 clear_mpint(&i43);
 clear_mpprime(&p97);
```

10.6 Exampel 2

Compute $(34 \times 43^{55}) \mod 97$.

```
MPPRIME p97;
MPINT i34, i43, i55;

// Initialize
init_mpint(&i34);
init_mpint(&i43);
init_mpint(&i55);
init_mpprime(&p97);

// Set value
word_mpint(&i34, 34, 1);
word_mpint(&i43, 43, 1);
word_mpint(&i55, 55, 1);
word_mpint(&i55, 55, 1);
word_mpint(&(p97.num), 97, 1);
precompprime_mpint(&p97);
```

```
17  // To Montgomery space
18  to_montgomery_mpint(&i34, &p97);
19  
20  // Exponenciation
21  powmod_mpint(&i43, &i55, &p97, MONTGOMERY);
22  
23  // print intermediate result
24  print_mpint(&i43);
25  
26  // Multiplication
27  montgomery_mul_mpint(&i34, &i43, &p97);
28  
29  // Back to real value
30  from_montgomery_mpint(&i34, &p97);
31  
32  // print result
33  print_mpint(&i34);
34  
35  // clear memory
36  clear_mpint(&i34);
37  clear_mpint(&i34);
38  clear_mpint(&i43);
39  clear_mpint(&i55);
30  clear_mpprime(&p97);
```

11 bits operations

11.1 rshift_mpint

Prototype

```
bool8 rshift_mpint(MPINT* x, int32 shift);
```

Description Shift shift bits on the right.

Note For negative number, the absolute value is shifted and the sign stays negative.

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

11.2 rshiftw_mpint

Prototype

```
bool8 rshiftw_mpint(MPINT* x, int32 shift);
```

Description Shift shift HALF_WORD on the right.

Note This function is not hardware independant.

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

11.3 lshift_mpint

Prototype

```
bool8 lshift_mpint(MPINT* x, int32 shift);
```

Description Shift shift bits on the left.

Note For negative number, the absolute value is shifted and the sign stays negative.

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

11.4 safelshift_mpint

Prototype

```
bool8 lshift_mpint(MPINT* x, int32 shift);
```

Description Shift *shift* bits on the left without extending the *MPINT*.

Note The maximum value for *shift* is HW_BITS . It used for example in the *unsigndiv_mpint* function to ensure that the high order bits of the high order $HALF_WORD$ is 1.

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

12 Random

The MPINT library is using the pseudo random generator ISAAC.

A random context is used has parameter of each function, see the following example on how to create a context:

```
#include <random.h>

randctx ctx;
int i;
byte* wt;

// seed array of size RANDIZL * sizeof(uint32)
wt = (byte *)ctx.randrsl;

// set a seed
for (i = 0 ; i < RANDSIZL * sizeof(uint32) ; i++) {
    *wt++ = i & 0xFF;
}

// Init the context TRUE is set to use the seed provided.
// FALSE create a default context
randinit(&ctx, TRUE);</pre>
```

The function $init_context(randctx^*)$ can also be used. It seeds the context with a random value taken from a random pool inside the Xinu kernel¹.

12.1 rand_mpint

Prototype

```
bool8 rand_mpint(MPINT *x, int32 length, randctx* ctx);
```

¹It is still experimental, the quality of the randomness may not be perfect

 $\textbf{Description} \ \text{Create a random} \ MPINT \ \text{with} \ length \ HALF_WORD \ \text{with a uniform probability law}.$

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

$12.2 \quad randmod_mpint$

Prototype

```
bool8 randmod_mpint(MPINT* k, MPINT* q, randctx* ctx);
```

Description Create a random MPINT in the range 0 to q-1 with a uniform probability law.

Return The function returns TRUE if it has been successful, FALSE if an error occurred.

13 Performance evaluation