Buffers

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspace-api][media][v41]buffer.rst, line 2)

Unknown directive type "cnamespace".

.. c:namespace:: V4L
```

A buffer contains data exchanged by application and driver using one of the Streaming I/O methods. In the multi-planar API, the data is held in planes, while the buffer structure acts as a container for the planes. Only pointers to buffers (planes) are exchanged, the data itself is not copied. These pointers, together with meta-information like timestamps or field parity, are stored in a struct :ctype:'v412_buffer', argument to the ref:'VIDIOC_QUERYBUF', ref:'VIDIOC_QBUF <VIDIOC_QBUF>' and ref:'VIDIOC_DQBUF <VIDIOC_QBUF>' ioctl. In the multi-planar API, some plane-specific members of struct :ctype:'v412_buffer', such as pointers and sizes for each plane, are stored in struct :ctype:'v412_plane' instead. In that case, struct :ctype:'v412_buffer' contains an array of plane structures.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] buffer.rst, line 10); backlink

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 10); backlink

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 10); backlink

Unknown interpreted text role 'ref'.

 $System\ Message:\ ERROR/3\ (\ D:\ onboarding\ -resources\ \ sample-onboarding\ -resources\ \ linux-master\ \ [Documentation\]\ [userspace-api]\ [media]\ [v41]\ buffer.rst,\ line\ 10);\ backlink$

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 10); backlink

Unknown interpreted text role "c:type".

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 10); backlink

Unknown interpreted text role "c:type".

Dequeued video buffers come with timestamps. The driver decides at which part of the frame and with which clock the timestamp is taken. Please see flags in the masks V4L2_BUF_FLAG_TIMESTAMP_MASK and V4L2_BUF_FLAG_TSTAMP_SRC_MASK in ref. buffer-flags. These flags are always valid and constant across all buffers during the whole video stream. Changes in these flags may take place as a side effect of ref. VIDIOC_S_INPUT <VIDIOC_G_INPUT> or ref. VIDIOC_S_OUTPUT <VIDIOC_G_OUTPUT> however. The V4L2_BUF_FLAG_TIMESTAMP_COPY timestamp type which is used by e.g. on mem-to-mem devices is an exception to the rule: the timestamp source flags are copied from the OUTPUT video buffer to the CAPTURE video buffer.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] buffer.rst, line 24); backlink

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 24); backlink

Unknown interpreted text role 'ref'.

Unknown interpreted text role "ref".

Interactions between formats, controls and buffers

V4L2 exposes parameters that influence the buffer size, or the way data is laid out in the buffer. Those parameters are exposed through both formats and controls. One example of such a control is the V4L2_CID_ROTATE control that modifies the direction in which pixels are stored in the buffer, as well as the buffer size when the selected format includes padding at the end of lines.

The set of information needed to interpret the content of a buffer (e.g. the pixel format, the line stride, the tiling orientation or the rotation) is collectively referred to in the rest of this section as the buffer layout.

Controls that can modify the buffer layout shall set the V4L2 CTRL FLAG MODIFY LAYOUT flag.

Modifying formats or controls that influence the buffer size or layout require the stream to be stopped. Any attempt at such a modification while the stream is active shall cause the ioctl setting the format or the control to return the EBUSY error code. In that case drivers shall also set the V4L2_CTRL_FLAG_GRABBED flag when calling :c:func: VIDIOC_QUERYCTRL' or :c:func: VIDIOC_QUERY_EXT_CTRL' for such a control while the stream is active.

System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 54); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 54); backlink

Unknown interpreted text role "c:func".

Note

The c:finc:'VIDIOC_S_SELECTION' ioctl can, depending on the hardware (for instance if the device doesn't include a scaler), modify the format in addition to the selection rectangle. Similarly, the c:finc:'VIDIOC_S_INPUT', c:finc:'VIDIOC_S_OUTPUT', c:finc:'VIDIOC_S_STD' and c:finc:'VIDIOC_S_DV_TIMINGS' ioctls can also modify the format and selection rectangles. When those ioctls result in a buffer size or layout change, drivers shall handle that condition as they would handle it in the c:finc:'VIDIOC_S_FMT' ioctl in all cases described in this section

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master]
[Documentation] [userspace-api] [media] [v41] buffer.rst, line 64); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master]
[Documentation] [userspace-api] [media] [v41]buffer.rst, line 64); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master]
[Documentation] [userspace-api] [media] [v41]buffer.rst, line 64); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 64); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master]
[Documentation] [userspace-api] [media] [v41] buffer.rst, line 64); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master]
[Documentation] [userspace-api] [media] [v41] buffer.rst, line 64); backlink

Unknown interpreted text role "c:func".

Controls that only influence the buffer layout can be modified at any time when the stream is stopped. As they don't influence the buffer size, no special handling is needed to synchronize those controls with buffer allocation and the V4L2_CTRL_FLAG_GRABBED flag is cleared once the stream is stopped.

Formats and controls that influence the buffer size interact with buffer allocation. The simplest way to handle this is for drivers to always require buffers to be reallocated in order to change those formats or controls. In that case, to perform such changes, userspace applications shall first stop the video stream with the c:finc: VIDIOC_STREAMOFF' ioctl if it is running and free all buffers with the c:finc: VIDIOC_REQBUFS' ioctl if they are allocated. After freeing all buffers the V4L2_CTRL_FLAG_GRABBED flag for controls is cleared. The format or controls can then be modified, and buffers shall then be reallocated and the stream restarted. A typical ioctl sequence is

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 79); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 79); backlink

Unknown interpreted text role "c:func".

- 1. VIDIOC STREAMOFF
- 2. VIDIOC_REQBUFS(0)
- 3. VIDIOC S EXT CTRLS
- 4. VIDIOC S FMT
- 5. VIDIOC_REQBUFS(n)
- 6. VIDIOC_QBUF
- 7. VIDIOC STREAMON

The second :c:fine: VIDIOC_REQBUFS` call will take the new format and control value into account to compute the buffer size to allocate. Applications can also retrieve the size by calling the :c:fine: VIDIOC_G_FMT` ioctl if needed.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 98); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 98); backlink

Unknown interpreted text role "c:func".

Note

The API doesn't mandate the above order for control (3.) and format (4.) changes. Format and controls can be set in a different order, or even interleaved, depending on the device and use case. For instance some controls might behave differently for different pixel formats, in which case the format might need to be set first.

When reallocation is required, any attempt to modify format or controls that influences the buffer size while buffers are allocated shall cause the format or control set ioctl to return the EBUSY error. Any attempt to queue a buffer too small for the current format or controls shall cause the :c:fimc:'VIDIOC_QBUF' ioctl to return a EINVAL error.

System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 110); backlink

Unknown interpreted text role "c:func".

Buffer reallocation is an expensive operation. To avoid that cost, drivers can (and are encouraged to) allow format or controls that influence the buffer size to be changed with buffers allocated. In that case, a typical ioctl sequence to modify format and controls is

- VIDIOC_STREAMOFF
- VIDIOC_S_EXT_CTRLS VIDIOC_S_FMT 2.
- 3.
- VIDIOC QBUF 4.
- VIDIOC STREAMON

For this sequence to operate correctly, queued buffers need to be large enough for the new format or controls. Drivers shall return a ENOSPC error in response to format change (x:fine: VIDIOC_S_FMT') or control changes (x:fine: VIDIOC_S_CTRL') or .c.func: VIDIOC_S_EXT_CTRLS') if buffers too small for the new format are currently queued. As a simplification, drivers are allowed to return a EBUSY error from these loctls if any buffer is currently queued, without checking the queued buffers sizes.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linuxmaster\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspaceapi] [media] [v41]buffer.rst, line 127); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linuxmaster\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspaceapi] [media] [v41]buffer.rst, line 127); backlink

Unknown interpreted text role "c:func".

 $System\,Message:\,ERROR/3\,(\texttt{D:\noboarding-resources}) a \textit{mple-onboarding-resources} \ \, \texttt{linux-onboarding-resources}) and \textit{more of the property of the pr$ master\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspaceapi] [media] [v41] buffer.rst, line 127); backlink

Unknown interpreted text role "c:func".

Additionally, drivers shall return a EINVAL error from the :c:func: VIDIOC QBUF ioctl if the buffer being queued is too small for the current format or controls. Together, these requirements ensure that queued buffers will always be large enough for the configured format and controls.

 $System\,Message:\,ERROR/3\,(\texttt{D:}\nonling-resources}) a \textit{mple-onboarding-resources} \ in \textit{ux-onboarding-resources}) and \textit{upper position}. The description of the de$ master\Documentation\userspace-api\media\v4\[linux-master][Documentation][userspaceapi] [media] [v41]buffer.rst, line 135); backlink Unknown interpreted text role "c:func".

Userspace applications can query the buffer size required for a given format and controls by first setting the desired control values and then trying the desired format. The :c:func: VIDIOC TRY FMT ioctl will return the required buffer size.

 $System\,Message:\,ERROR/3\, (\hbox{D:$\oonboarding-resources}) sample-onboarding-resources \verb|\linux-resources|| to the control of th$ master\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspaceapi] [media] [v41]buffer.rst, line 140); backlink

Unknown interpreted text role "c:func".

- VIDIOC_S_EXT_CTRLS(x) 1.
- 2.
- VIDIOC_TRY_FMT()
 VIDIOC_S_EXT_CTRLS(y) 3.
- VIDIOC_TRY_FMT()

The :c:func: VIDIOC CREATE BUFS' ioctl can then be used to allocate buffers based on the queried sizes (for instance by allocating a set of buffers large enough for all the desired formats and controls, or by allocating separate set of appropriately sized buffers for each use case).

master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspaceapi] [media] [v41]buffer.rst, line 150); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linuxmaster\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspaceapi] [media] [v41]buffer.rst, line 155)

Unknown directive type "c:type".

.. c:type:: v412 buffer

master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspaceapi] [media] [v41]buffer.rst, line 160)

Unknown directive type "tabularcolumns".

.. tabularcolumns:: $|p{2.9cm}|p{2.4cm}|p{12.0cm}|$

 $System\,Message:\,ERROR/3\, (\texttt{D:} \ \texttt{onboarding-resources} \ \texttt{sample-onboarding-resources} \ \texttt{linux-onboarding-resources})$ master\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspaceapi] [media] [v41] buffer.rst, line 162)

Unknown directive type "cssclass".

.. cssclass:: longtable

 $System\,Message:\,ERROR/3\,(\text{D:}\coloreding-resources}\coloreding-resources\coloreding-resources)$ master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-

```
api] [media] [v41] buffer.rst, line 164)
Unknown directive type "flat-table".
    .. flat-table:: struct v412 buffer
        :header-rows: 0
        :stub-columns: 0
        :widths:
          - _u32
- ``index``
           - Number of the buffer, set by the application except when calling
              :ref:`VIDIOC_DQBUF <VIDIOC_QBUF>`, then it is set by the
              driver. This field can range from zero to the number of buffers
             allocated with the :ref:`VIDIOC_REQBUFS` ioctl
             (struct :c:type:`v412_requestbuffers`
``count``), plus any buffers allocated with
             :ref:`VIDIOC CREATE BUFS` minus one.
        * - __u32
- ``type`
           - Type of the buffer, same as struct
:c:type:`v412_format` ``type`` or struct
:c:type:`v412_requestbuffers` ``type``, set
             by the application. See :c:type:`v412_buf_type`
        * - _u32
- ``bytesused``
           - The number of bytes occupied by the data in the buffer. It depends
             on the negotiated data format and may change with each buffer for % \left( 1\right) =\left( 1\right) \left( 1\right) 
             compressed variable size data like JPEG images. Drivers must set this field when ``type`` refers to a capture stream, applications
             when it refers to an output stream. If the application sets this to 0 for an output stream, then ``bytesused`` will be set to the
              size of the buffer (see the ``length`` field of this struct) by
              the driver. For multiplanar formats this field is ignored and the
               'planes' pointer is used instead.
         * - __u32
- ``flags`
           - Flags set by the application or driver, see :ref:`buffer-flags`.
         * - __u32
- ``field``
           - Indicates the field order of the image in the buffer, see
             :c:type:`v412_field`. This field is not used when the buffer contains VBI data. Drivers must set it when ``type`` refers
                                                                              refers to a
             capture stream, applications when it refers to an output stream.
         * - struct timeval
             ``timestamp`
           - For capture streams this is time when the first data byte was
             captured, as returned by the :c:func:`clock gettime()`
                                                                                  function
              for the relevant clock id; see ``V4L2 BUF FLAG TIMESTAMP *``
              :ref:`buffer-flags`. For output streams the driver stores the
              time at which the last data byte was actually sent out in the
              ``timestamp`` field. This permits applications to monitor the
             drift between the video and system clock. For output streams that use ``V4L2_BUF_FLAG_TIMESTAMP_COPY`` the application has to fill
              in the timestamp which will be copied by the driver to the capture
             stream.
         * - struct :c:type: `v412 timecode `
           - ``timecode
           - When the ``V4L2 BUF FLAG TIMECODE`` flag is set in ``flags``, this
             structure contains a frame timecode. In
              :c:type:`V4L2 FIELD ALTERNATE <v412 field>` mode the top and
              bottom field contain the same timecode. Timecodes are intended to
             help video editing and are typically recorded on video tapes, but
             also embedded in compressed formats like MPEG. This field is independent of the ``timestamp`` and ``sequence`` fields.
             independent of the `
           - u32
- ``sequence`
```

- Set by the driver, counting the frames (not fields!) in sequence.

This field is set for both input and output devices.

```
* - :cspan:`2`
    In :c:type:`V4L2_FIELD_ALTERNATE <v4l2_field>` mode the top and
    bottom field have the same sequence number. The count starts at
    zero and includes dropped or repeated frames. A dropped frame was
    received by an input device but could not be stored due to lack of
    free buffer space. A repeated frame was displayed again by an
    output device because the application \operatorname{did} not pass new data in
    time.
    .. note::
       This may count the frames received e.g. over USB, without
        taking into account the frames dropped by the remote hardware due
        to limited compression throughput or bus bandwidth. These devices
        identify by not enumerating any video standards, see
        :ref:`standard`.
* - __u32
- ``memory``
  - This field must be set by applications and/or drivers in
    accordance with the selected I/O method. See :c:type:`v412_memory`
* - union {
  - ``m'
* - _u32
- ``offset`
  - For the single-planar API and when ``memory`` is
     ``V4L2 MEMORY MMAP`` this is the offset of the buffer from the
    start of the device memory. The value is returned by the driver
    and apart of serving as parameter to the
    :c:func:`mmap()` function not useful for applications.
    See :ref:`mmap` for details
* - unsigned long
    ``userptr`
  - For the single-planar API and when ``memory`` is
   ``V4L2_MEMORY_USERPTR`` this is a pointer to the buffer (casted to
    unsigned long type) in virtual memory, set by the application. See
    :ref:`userp` for details.
* - struct v412_plane
    ``*planes`
  - When using the multi-planar API, contains a userspace pointer to
    an array of struct :c:type:`v412 plane`. The size of the array should be put in the ``length`` field of this
    struct :c:type:`v412 buffer` structure.
  - ``fd`
  - For the single-plane API and when ''memory'' is
     `V4L2_MEMORY_DMABUF`` this is the file descriptor associated with
    a DMABUF buffer.
* - }
 - _u32
- ``length``
* _
  - Size of the buffer (not the payload) in bytes for the
    single-planar API. This is set by the driver based on the calls to
    :ref:`VIDIOC REQBUFS` and/or
    :ref:`VIDIOC CREATE BUFS`. For the
    multi-planar API the application sets this to the number of
    elements in the ``planes`` array. The driver will fill in the
   actual number of valid elements in that array.
  - _u32
- ``reserved2`
  - A place holder for future extensions. Drivers and applications
   must set this to 0.
  - _u32
- ``request_fd`
  - The file descriptor of the request to queue the buffer to. If the flag ``V4L2_BUF_FLAG_REQUEST_FD`` is set, then the buffer will be
    queued to this request. If the flag is not set, then this field will
    be ignored.
    The ``V4L2_BUF_FLAG_REQUEST_FD`` flag and this field are only used by
    :ref:`ioctl VIDIOC_QBUF <VIDIOC_QBUF>` and ignored by other ioctls that
    take a :c:type:`v412_buffer` as argument.
    Applications should not set ``V4L2_BUF_FLAG_REQUEST_FD`` for any ioctls other than :ref: `VIDIOC_QBUF <VIDIOC_QBUF>`.
    If the device does not support requests, then ``EBADR`` will be returned. If requests are supported but an invalid request file descriptor is given, then ``EINVAL`` will be returned.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 312)

Unknown directive type "c:type".

```
.. c:type:: v4l2_plane
```

struct v4l2_plane

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspace-api][media][v41]buffer.rst, line 317)

Unknown directive type "tabularcolumns".

.. tabularcolumns:: |p{3.5cm}|p{3.5cm}|p{10.3cm}|
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-
master\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspace-
api][media][v41]buffer.rst, line 319)
Unknown directive type "cssclass".
.. cssclass:: longtable
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linuxmaster\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspaceapi] [media] [v41] buffer.rst, line 321) Unknown directive type "flat-table". .. flat-table:: :header-rows: 0 :stub-columns: 0 :widths: * - __u32 - ``bytesused`` - The number of bytes occupied by data in the plane (its payload). Drivers must set this field when ``type`` refers to a capture stream, applications when it refers to an output stream. If the application sets this to 0 for an output stream, then 'bytesused' will be set to the size of the plane (see the ``length`` field of this struct) by the driver. Note that the actual image data starts at ``data_offset`` which may not be 0.- _u32 - ``length` - Size in bytes of the plane (not its payload). This is set by the driver based on the calls to :ref:`VIDIOC REQBUFS` and/or :ref: `VIDIOC CREATE BUFS`. * - union { - ``m` - _u32 - ``mem_offset`` - When the memory type in the containing struct :c:type:`v412_buffer` is ``V4L2_MEMORY_MMAP``, this similar to the ``offset`` field in struct :c:type:`v412_buffer`. * - unsigned long - ``userptr`` - When the memory type in the containing struct
:c:type:`v412_buffer` is ``V4L2_MEMORY_USERPTR``, this is a userspace pointer to the memory allocated for this plane by an application. * - int - ``fd`` this is a file descriptor associated with a DMABUF buffer, similar to the ``fd`` field in struct :c:type:`v412_buffer`. * - } * - __u32 - ``data_offset`` - Offset in bytes to video data in the plane. Drivers must set this field when ``type`` refers to a capture stream, applications when it refers to an output stream. .. note:: That data_offset is included in ``bytesused``. So the size of the image in the plane is ``bytesused``-``data_offset`` at offset ``data_offset`` from the start of the plane. * - _u32 - ``reserved[11]`` - Reserved for future use. Should be zeroed by drivers and applications.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] buffer.rst, line 385)

Unknown directive type "c:type".

.. c:type:: v412_buf_type
```

enum v4l2_buf_type

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspace-api][media][v41]buffer.rst, line 390)

Unknown directive type "cssclass".

.. cssclass:: longtable
```

```
System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 392)

Unknown directive type "tabularcolumns".

... tabularcolumns:: |p{7.8cm}|p{0.6cm}|p{8.9cm}|
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 394)

Unknown directive type "flat-table".

```
.. flat-table::
   :header-rows: 0
   :stub-columns: 0
                   4 1 9
   :widths:
    * - ``V4L2 BUF_TYPE_VIDEO_CAPTURE``
     - Buffer of a single-planar video capture stream, see
   :ref:`capture`.
* - ``V4L2_BUF_TYPE_VIDEO_CAPTURE_MPLANE``
      - Buffer of a multi-planar video capture stream, see
   :ref:`capture`.
* - ``V4L2_BUF_TYPE_VIDEO_OUTPUT``
      - Buffer of a single-planar video output stream, see
    :ref:`output`.
* - ``V4L2_BUF_TYPE_VIDEO_OUTPUT_MPLANE``
     - 10
     - Buffer of a multi-planar video output stream, see :ref:`output`.
    * - ``V4L2_BUF_TYPE_VIDEO_OVERLAY
     - Buffer for video overlay, see :ref:`overlay`.
    * - ``V4L2_BUF_TYPE_VBI_CAPTURE`
     - 4
     - Buffer of a raw VBI capture stream, see :ref:`raw-vbi`.
    * - ``V4L2_BUF_TYPE_VBI_OUTPUT`
     - 5
     - Buffer of a raw VBI output stream, see :ref:`raw-vbi`.
    * - ``V4L2_BUF_TYPE_SLICED_VBI_CAPTURE
     - 6
     - Buffer of a sliced VBI capture stream, see :ref:`sliced`.
    * - ``V4L2_BUF_TYPE_SLICED_VBI_OUTPUT`
     - Buffer of a sliced VBI output stream, see :ref:`sliced`.
    * - ``V4L2_BUF_TYPE_VIDEO_OUTPUT_OVERLAY
     - 8
     - Buffer for video output overlay (OSD), see :ref:`osd`.
         `V4L2_BUF_TYPE_SDR_CAPTURE`
     - 11
   :ref:`sdr`
     - Buffer for Software Defined Radio (SDR) capture stream, see
         `V4L2_BUF_TYPE_SDR_OUTPUT``
     - 12
   :ref:`sdr`
* - ``\\
     - Buffer for Software Defined Radio (SDR) output stream, see
         `V4L2_BUF_TYPE_META_CAPTURE``
     - 13
     - Buffer for metadata capture, see :ref:`metadata`.
    * - ``V4L2_BUF_TYPE_META_OUTPUT
```

```
- 14 - Buffer for metadata output, see :ref:`metadata`.
```

Buffer Flags

```
System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] buffer.rst, line 457)

Unknown directive type "tabularcolumrs".

.. tabularcolumns:: |p{6.5cm}|p{1.8cm}|p{9.0cm}|
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linuxmaster\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspaceapi][media][v41]buffer.rst, line 459)
Unknown directive type "cssclass".
... cssclass:: longtable

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linuxmaster\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspaceapi] [media] [v41] buffer.rst, line 461) Unknown directive type "flat-table". .. flat-table:: :header-rows: 0 :stub-columns: 0 :widths: 65 18 70 * .. _`V4L2-BUF-FLAG-MAPPED`: - ``V4L2_BUF_FLAG_MAPPED`` - 0x0000001 - The buffer resides in device memory and has been mapped into the application's address space, see :ref:`mmap` for details. Drivers set or clear this flag when the :ref:`VIDIOC_QUERYBUF`,
:ref:`VIDIOC_QBUF` or :ref:`VIDIOC_DQBUF <VIDIOC_QBUF>` ioctl is called. Set by the driver. * .. _`V4L2-BUF-FLAG-QUEUED`: - ``V4L2_BUF_FLAG_QUEUED`` -0×000000002 - Internally drivers maintain two buffer queues, an incoming and outgoing queue. When this flag is set, the buffer is currently on the incoming queue. It automatically moves to the outgoing queue after the buffer has been filled (capture devices) or displayed (output devices). Drivers set or clear this flag when the ``VIDIOC_QUERYBUF`` ioctl is called. After (successful) calling ``VIDIOC QBUF``\ ioctl it is always set and after the `VIDIOC DQBUF`` always cleared. * .. _`V4L2-BUF-FLAG-DONE`: - ``V4L2_BUF_FLAG_DONE`` -0x000000004- When this flag is set, the buffer is currently on the outgoing queue, ready to be dequeued from the driver. Drivers set or clear this flag when the ``VIDIOC QUERYBUF`` ioctl is called. After calling the ``VIDIOC QBUF`` or ``VIDIOC DQBUF`` it is always cleared. Of course a buffer cannot be on both queues at the same time, the ``V4L2_BUF_FLAG_QUEUED`` and ``V4L2_BUF_FLAG_DONE`` flag are mutually exclusive. They can be both cleared however, then the buffer is in "dequeued" state, in the application domain so to say.
* .. _`V4L2-BUF-FLAG-ERROR`: - ``V4L2_BUF_FLAG_ERROR`` - When this flag is set, the buffer has been dequeued successfully, although the data might have been corrupted. This is recoverable, streaming may continue as normal and the buffer may be reused normally. Drivers set this flag when the ``VIDIOC_DQBUF`` ioctl is called. * .. _`V4L2-BUF-FLAG-IN-REQUEST`: - ``V4L2_BUF_FLAG_IN_REQUEST`` -0x00000080- This buffer is part of a request that hasn't been queued yet.

* .. _`V4L2-BUF-FLAG-KEYFRAME`:

```
- ``V4L2_BUF_FLAG_KEYFRAME``
  -0 \times 000000008
  - Drivers set or clear this flag when calling the ``VIDIOC_DQBUF`
    ioctl. It may be set by video capture devices when the \operatorname{buffer}
    contains a compressed image which is a key frame (or field), i. e.
    can be decompressed on its own. Also known as an I-frame. Applications can set this bit when ``type`` refers to an output
    stream.
* .. _`V4L2-BUF-FLAG-PFRAME`:
  - ``V4L2 BUF FLAG PFRAME``
  -0 \times 00000010
  - Similar to ``V4L2_BUF_FLAG_KEYFRAME`` this flags predicted frames
    or fields which contain only differences to a previous key frame. Applications can set this bit when ``type`` refers to an output
    stream.
* .. _`V4L2-BUF-FLAG-BFRAME`:
  - ``V4L2 BUF_FLAG_BFRAME``
  -0x00000020
  - Similar to ``V4L2 BUF FLAG KEYFRAME`` this flags a bi-directional
    predicted frame or field which contains only the differences
    between the current frame and both the preceding and following key
    frames to specify its content. Applications can set this bit when
      `type``
              refers to an output stream.
* .._`V4L2-BUF-FLAG-TIMECODE`:
  - ``V4L2 BUF FLAG TIMECODE``
  - 0x00000100
  - The ``timecode`` field is valid. Drivers set or clear this flag when the ``VIDIOC_DQBUF`` ioctl is called. Applications can set this bit and the corresponding ``timecode`` structure when
     `type`` refers to an output stream.
* .. _ `V4L2-BUF-FLAG-PREPARED`:
  - ``V4L2_BUF_FLAG_PREPARED`
  -0x00000400
  - The buffer has been prepared for I/O and can be queued by the
    application. Drivers set or clear this flag when the
    :ref: `VIDIOC QUERYBUF`
    :ref: `VIDIOC PREPARE BUF <VIDIOC QBUF>`,
    :ref:`VIDIOC_OBUF` or
:ref:`VIDIOC_DQBUF <VIDIOC_OBUF>` ioctl is called.
* .. `V4L2-BUF-FLAG-NO-CACHE-INVALIDATE`:
  - ``V4L2_BUF_FLAG_NO_CACHE_INVALIDATE``
  - 0x00000800
  - Caches do not have to be invalidated for this buffer. Typically
    applications shall use this flag if the data captured in the
    buffer is not going to be touched by the CPU, instead the buffer
    will, probably, be passed on to a DMA-capable hardware unit for
    further processing or output. This flag is ignored unless the
    queue is used for :ref: `memory mapping <mmap>` streaming I/O and
    reports :ref: `V4L2_BUF_CAP_SUPPORTS_MMAP_CACHE_HINTS
    <V4L2-BUF-CAP-SUPPORTS-MMAP-CACHE-HINTS> capability.
* .. `V4L2-BUF-FLAG-NO-CACHE-CLEAN`:
  - ``V4L2_BUF_FLAG_NO_CACHE_CLEAN``
  -0x0000\overline{1000}
  - Caches do not have to be cleaned for this buffer. Typically
    applications shall use this flag for output buffers if the data in
    this buffer has not been created by the CPU but by some
    DMA-capable unit, in which case caches have not been used. This flag
    is ignored unless the queue is used for :ref:`memory mapping <mmap>
    streaming I/O and reports :ref: `V4L2_BUF_CAP_SUPPORTS MMAP_CACHE_HINTS <V4L2_BUF_CAP-SUPPORTS-MMAP-CACHE-HINTS>` capability.
* .. _`V4L2-BUF-FLAG-M2M-HOLD-CAPTURE-BUF`:
  - ``V4L2 BUF FLAG_M2M_HOLD_CAPTURE_BUF``
  -0x00000200
  - Only valid if struct :c:type:`v412_requestbuffers` flag ``V4L2_BUF_CAP_SUPPORTS_M2M_HOLD_CAPTURE
    set. It is typically used with stateless decoders where multiple
    output buffers each decode to a slice of the decoded frame.
    Applications can set this flag when queueing the output buffer
    to prevent the driver from dequeueing the capture buffer after
    the output buffer has been decoded (i.e. the capture buffer is
    'held'). If the timestamp of this output buffer differs from that
    of the previous output buffer, then that indicates the start of a
new frame and the previously held capture buffer is dequeued.  
* .. _`V4L2-BUF-FLAG-LAST`:
  - ``V4L2_BUF_FLAG_LAST``
  - 0x00100000
  - Last buffer produced by the hardware. mem2mem codec drivers set
    this flag on the capture queue for the last buffer when the :ref: `VIDIOC QUERYBUF` or
    ref; VIDIOC_DQBUF <VIDIOC_QBUF>` ioctl is called. Due to hardware limitations, the last buffer may be empty. In this case the driver will set the ``bytesused`` field to 0, regardless of
    the format. Any subsequent call to the
    :ref:'VIDIOC_DQBUF <VIDIOC_QBUF>' ioctl will not block anymore, but return an ``EPIPE`` error code.
* .. _`V4L2-BUF-FLAG-REQUEST-FD`:
```

```
- ``V4L2_BUF_FLAG_REQUEST_FD``
  -0x0080\overline{0}000
  - The ``request_fd`` field contains a valid file descriptor.
* .. _ `V4L2-BUF-FLAG-TIMESTAMP-MASK`:
  - ``V4L2_BUF_FLAG_TIMESTAMP_MASK``
  - 0x0000e000
  - Mask for timestamp types below. To test the timestamp type, mask
   out bits not belonging to timestamp type by performing a logical and operation with buffer flags and timestamp mask.
* .. _ `V4L2-BUF-FLAG-TIMESTAMP-UNKNOWN`:
  - ``V4L2_BUF_FLAG_TIMESTAMP_UNKNOWN`
  -0x00000000
  - Unknown timestamp type. This type is used by drivers before Linux 3.9 and may be either monotonic (see below) or realtime (wall
    clock). Monotonic clock has been favoured in embedded systems
    whereas most of the drivers use the realtime clock. Either kinds
    of timestamps are available in user space via :c:func:`clock gettime` using clock IDs ``CLOCK MONOTONIC``
    :c:func:`clock gettime` using clock IDs and ``CLOCK REALTIME``, respectively.
    and `
* .. _`V4L2-BUF-FLAG-TIMESTAMP-MONOTONIC`:
  - ``V4L2_BUF_FLAG_TIMESTAMP_MONOTONIC``
  -0x0000\overline{2}000
  - The buffer timestamp has been taken from the ``CLOCK MONOTONIC``
    clock. To access the same clock outside V4L2, use
    :c:func:`clock gettime`.
 .._`V4L2-BUF-FLAG-TIMESTAMP-COPY`:
  - ``V4L2 BUF FLAG TIMESTAMP COPY``
  -0x0000\overline{4}000
  - The CAPTURE buffer timestamp has been taken from the corresponding
   OUTPUT buffer. This flag applies only to mem2mem devices.
* .. _`V4L2-BUF-FLAG-TSTAMP-SRC-MASK`:
  - ``V4L2_BUF_FLAG_TSTAMP_SRC_MASK``
  -0x00070000
  - Mask for timestamp sources below. The timestamp source defines the
    point of time the timestamp is taken in relation to the frame. Logical 'and' operation between the ``flags`` field and ``V4L2_BUF_FLAG_TSTAMP_SRC_MASK`` produces the value of the
    timestamp source. Applications must set the timestamp source when
      `type`` refers to an output stream and
    ``V4L2_BUF_FLAG_TIMESTAMP_COPY`` is set.
* .. _`V4L2-BUF-FLAG-TSTAMP-SRC-EOF`:
  - ``V4L2_BUF_FLAG_TSTAMP_SRC_EOF``
  -0x00000000
  - {\tt End} Of {\tt Frame}. The buffer timestamp has been taken when the last
    pixel of the frame has been received or the last pixel of the
    frame has been transmitted. In practice, software generated
    timestamps will typically be read from the clock a small amount of
    time after the last pixel has been received or transmitten,
   depending on the system and other activity in it.
* .. _`V4L2-BUF-FLAG-TSTAMP-SRC-SOE`:
  - ``V4L2_BUF_FLAG_TSTAMP_SRC_SOE``
  - 0x00010000
  - Start Of Exposure. The buffer timestamp has been taken when the
    exposure of the frame has begun. This is only valid for the
      `V4L2_BUF_TYPE_VIDEO_CAPTURE`` buffer type.
```

enum v4l2 memory

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspace-api][media][v41]buffer.rst, line 682)
Unknown directive type "tabularcolumns".
.. tabularcolumns:: |p{5.0cm}|p{0.8cm}|p{11.5cm}|
```

```
- 1- The buffer is used for :ref:`memory mapping <mmap>` I/O.
```

* - ``V4L2_MEMORY_MMAP``

```
* - ``V4L2_MEMORY_USERPTR``
- 2
- The buffer is used for :ref:`user pointer <userp>` I/O.

* - ``V4L2_MEMORY_OVERLAY``
- 3
- [to do]
* - ``V4L2_MEMORY_DMABUF``
- 4
- The buffer is used for :ref:`DMA shared buffer <dmabuf>` I/O.
```

Memory Consistency Flags

```
System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\linux-
master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-
api] [media] [v41]buffer.rst, line 711)
Unknown directive type "tabularcolumns".
... tabularcolumns:: |p{7.0cm}|p{2.1cm}|p{8.4cm}|
```

```
System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\linux-
master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-
api] [media] [v41]buffer.rst, line 713)
Unknown directive type "cssclass".
... cssclass:: longtable
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 715)

Unknown directive type "flat-table".

```
.. flat-table::
   :header-rows: 0
   :stub-columns: 0
   * .. _`V4L2-MEMORY-FLAG-NON-COHERENT`:
     - ``V4L2 MEMORY_FLAG_NON_COHERENT``
     -0x00000001
      - A buffer is allocated either in coherent (it will be automatically
       coherent between the CPU and the bus) or non-coherent memory. The
       latter can provide performance gains, for instance the CPU cache
       sync/flush operations can be avoided if the buffer is accessed by the
       corresponding device only and the CPU does not read/write to/from that
       buffer. However, this requires extra care from the driver -- it must
       guarantee memory consistency by issuing a cache flush/sync when
       consistency is needed. If this flag is set V4L2 will attempt to
       allocate the buffer in non-coherent memory. The flag takes effect
       only if the buffer is used for :ref:`memory mapping <mmap>` I/O and the
       queue reports the :ref: `V4L2_BUF_CAP_SUPPORTS_MMAP_CACHE_HINTS
       <V4L2-BUF-CAP-SUPPORTS-MMAP-CACHE-HINTS>` capability.
```

Timecodes

The :c:type:'v412_buffer_timecode' structure is designed to hold a :ref.'smpte12m' or similar timecode. (struct :c:type:'timeval' timestamps are stored in the struct :c:type:'v412_buffer' timestamp field.)

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] buffer.rst, line 744); backlink
Unknown interpreted text role "ctype".
```

 $System \, Message: ERROR/3 \, (\mboarding-resources \sample-onboarding-resources \sample-onboarding-res$

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]buffer.rst, line 744); backlink

Unknown interpreted text role "c:type".

 $System\ Message: ERROR/3\ (D:\onboarding-resources\space-onboarding-resou$

Unknown interpreted text role "c:type".

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-
master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-
api] [media] [v41]buffer.rst, line 749)

Unknown directive type "c:type".

.. c:type:: v412_timecode
```

struct v4l2_timecode

```
System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] buffer.rst, line 754)
Unknown directive type "tabularcolumns".
.. tabularcolumns:: |p{1.4cm}|p{2.8cm}|p{13.1cm}|
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-
master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-
api] [media] [v41] buffer.rst, line 756)
Unknown directive type "flat-table".
   .. flat-table::
       :header-rows: 0
       :stub-columns: 0
                      1 1 2
       :widths:
       * - _u32
- ``type``
         - Frame rate the timecodes are based on, see :ref:`timecode-type`.
       * - __u32
- ``flags``
         - Timecode flags, see :ref:`timecode-flags`.
       * - _u8
- ``frames``
         - Frame count, 0 ... 23/24/29/49/59, depending on the type of
           timecode.
       * - _u8
- ``seconds`
         - Seconds count, 0 ... 59. This is a binary, not BCD number.
       * - _u8
- ``minutes`
         - Minutes count, 0 ... 59. This is a binary, not BCD number.
       * - _u8
- ``hours``
         - Hours count, 0 ... 29. This is a binary, not BCD number.
       * - _u8
- ``userbits``\ [4]
         - The "user group" bits from the timecode.
```

Timecode Types

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-
master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-
api] [media] [v41]buffer.rst, line 790)
Unknown directive type "flat-table".
   .. flat-table::
       :header-rows: 0
       :stub-columns: 0
                      3 1 4
       :widths:
       * - ``V4L2_TC_TYPE_24FPS``
         - 24 frames per second, i. e. film.
       * - ``V4L2_TC_TYPE_25FPS`
         - 25 frames per second, i. e. PAL or SECAM video.
       * - ``V4L2_TC_TYPE_30FPS
         - 30 frames per second, i. e. NTSC video.
       * - ``V4L2_TC_TYPE_50FPS`
```

```
-
* - ``V4L2_TC_TYPE_60FPS``
- 5
-
```

Timecode Flags

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspace-api][media][v41]buffer.rst, line 817)

Unknown directive type "tabularcolumns".

.. tabularcolumns:: |p{6.6cm}|p{1.4cm}|p{9.3cm}|
```

```
System\,Message:\,ERROR/3\,(\texttt{D:}\nonlineseques) + sample-onboarding-resources \verb|\linux-resources|| + sample-onboarding-resources|| + sample-onboarding-resources|| + sample-onboarding-resources|| + sample-onboar
master\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspace-
api][media][v41]buffer.rst, line 819)
Unknown directive type "flat-table".
               .. flat-table::
                               :header-rows: 0
                               :stub-columns: 0
                                                                                          3 1 4
                               :widths:
                               * - ``V4L2_TC_FLAG_DROPFRAME``
                                       - 0x0001
                                        - Indicates "drop frame" semantics for counting frames in 29.97 fps
                                               material. When set, frame numbers 0 and 1 at the start of each minute, except minutes 0, 10, 20, 30, 40, 50 are omitted from the
                                               count.
                                * - ``V4L2_TC_FLAG_COLORFRAME``
                                       - 0x0002
                                - The "color frame" flag.

* - ``V4L2_TC_USERBITS_field``

- 0x000C
                                - Field mask for the "binary group flags".
* - ``V4L2_TC_USERBITS_USERDEFINED``
                                       - 0x0000
                                       - Unspecified format.
                                * - ``V4L2_TC_USERBITS_8BITCHARS``
- 0x0008
```

- 8-bit ISO characters.