

Application control and post-processing

Riccardo Murri <riccardo.murri@uzh.ch>
S3IT: Services and Support for Science IT
University of Zurich

Application run states

Application lifecycle

```
$ ./grayscale.py lena.jpg
[...]

NEW 1/1 (100.0%)

RUNNING 0/1 (0.0%)

STOPPED 0/1 (0.0%)

SUBMITTED 0/1 (0.0%)

TERMINATED 0/1 (0.0%)

TERMINATING 0/1 (0.0%)

UNKNOWN 0/1 (0.0%)

total 1/1 (100.0%)
```

Application objects can be in one of several states.

(A session-based script prints a table of all managed applications and their states.)


```
>>> print (app.execution.state)
'TERMINATED'
```

The current state is stored in the .execution.state instance attribute.

Reference:

http://gc3pie.readthedocs.io/en/master/programmers/api/gc3libs.html#gc3libs.Run.state


Application lifecycle: state NEW



NEW is the state of "just created" Application objects.

The Application has not yet been sent off to a compute resource: it only exists locally.


Application lifecycle: state SUBMITTED



SUBMITTED applications have been successfully sent to a computational resource.


(The transition to *RUNNING* happens automatically, as we do not control the remote execution.)

Application lifecycle: state RUNNING



RUNNING state happens when the computational job associated to an application starts executing on the computational resource.


Application lifecycle: state STOPPED



A task is in *STOPPED* state when its execution has been blocked at the remote site and GC3Pie cannot recover automatically.

User or sysadmin intervention is required for a task to get out of STOPPED state.


Application lifecycle: state UNKNOWN



A task is in *UNKNOWN* state when GC3Pie can no longer monitor it at the remote site.

(As this might be due to network failures, jobs *can* get out of *UNKNOWN* automatically.)


Application lifecycle: state TERMINATING



TERMINATING state when a computational job has finished running, for whatever reason.

(Transition to TERMINATED only happens when fetch_output is called.)

Application lifecycle: state TERMINATED



A job is *TERMINATED* when its final output has been retrieved and is available locally.

The exit code of TERMINATED jobs can be inspected to find out whether the termination was successful or unsuccessful, or if the program was forcibly ended.

Post-processing

Post-processing features, I

When the remote computation is done, the terminated method of the application instance is called.

The path to the output directory is available as self.output_dir; if stdout and stderr have been captured, the **relative** paths to the capture files are available as self.stdout and self.stderr.

Post-processing features, II

For example, the following code logs a warning message if the standard error output is non-empty:

Exercise 5.A:

In the colorize.py script from Exercise 4.A, modify the ColorizeApp application to move the output picture file into directory /home/ubuntu/pictures. You might need to store the output file name to have it available when the application has terminated running.

(You might want to check out http://stackoverflow.com/a/8858026/459543 if you're unsure how to move/rename a file with Python.)

Termination status

A successful run or not?

There's a *single TERMINATED state*, whatever the task outcome. You have to inspect the "return code" to determine the cause of "task death".

Attribute '.execution.returncode' provides a numeric termination status (with the same format and meaning as the POSIX termination status).

The termination status combines two fields: the "termination signal" and the "exit code".

Termination signal, I

The .execution.signal instance attribute is non-zero if the program was killed by a signal (e.g., memory error / segmentation fault).

The .execution.signal instance attribute is zero only if the program run until termination. (**Beware!** This does not mean that it run *correctly*: just that it halted by itself.)

Termination signal, II

Read man 7 signal for a list of OS signals and their numeric values.

Note that GC3Pie overloads some signal codes (unused by the OS) to represent its own specific errors.

For instance, if program app was cancelled by the user, .execution.signal will take the value 121:

```
>>> print(app.execution.signal)
121
```

Reference: https://github.com/uzh/gc3pie/blob/master/gc3libs/_init__.py#L1579

Exit code

The .execution.exitcode instance attribute holds the numeric exitcode of the executed command, or None if the command has not finished running yet.

Note that the .execution.exitcode is guaranteed to have a valid value only if the .execution.signal attribute has the value 0.

The .execution.exitcode is the same exitcode that you would see when running a command directly in the terminal shell. (By convention, code 0 is successful termination, every other value indicates an error.)

Exercise 5.B:

Modify the grayscaling script ex2c (or the code it depends upon) so that, when a GrayscaleApp task has terminated execution, it prints:

- whether the program has been killed by a signal, and the signal number;
- whether the program has terminated by exiting, and the exit code.

Exercise 5.B+: (Bonus points) Abstract the verbose terminated method from exercise 3.B into an application class TermStatusApp.

Use Python class inheritance to add the TermStatusApp functionality into GrayscaleApp.

Application-specific configuration

Application classes may be tagged so that parts of the configuration file can be overridden just for them.

Suppose you tag the GrayscaleApp class by giving it this name:

```
class GrayscaleApp(Application):
   application_name = 'grayscale'
# [...]
```

then you can provide a specific VM image just for "grayscale" applications:

```
# in the GC3Pie config file:
[resource/sciencecloud]
# [...]
image_id=2b227d15-8f6a-42b0-b744-ede52ebe59f7
grayscale_image_id=0cca5346-ca12-4cb4-8007-8875c10cce02
```

Other configuration items that can be specialized are: instance_type, user_data (cloud), and prolog_file, epilog_file (batch-systems).

Exercise 5.C: (Difficult)

MATLAB has the annoying habit of exiting with code 0 even when some error occurred.

Write a MatlabApp application, which:

- is constructed by giving the path to a MATLAB '.m'
 script file, like this: app = MatlabApp("ra.m");
- Runs the following command:

```
matlab -nodesktop -nojvm file.m
where file.m is the file given to the MatlabApp()
constructor.
```

 captures the standard error output (stderr) of the MATLAB script and, if the string "Out of memory." occurs in it, sets the application exitcode to 11.

Verify that it works by running MATLAB script ra.m many times over. The script initializes a array of random size: for some values, the size exceeds the amount of available memory.