Table 1: Outlets for UAffinitiesComponent

GetUnspentPoints	
▶ Before	<pre>const uint8 OriginalPoints, uint8&amp;ReturnedPoints</pre>
► After	const uint8 OriginalPoints, const uint8 ReturnedPoints

SetUnspentPoints	
► Before	<pre>const uint8 OriginalPoints, const uint8 InputPoints, uint8&amp;SetPoints</pre>
► After	const uint8 OriginalPoints, const uint8 InputPoints, const uint8 SetPoints

Table 2: Outlets for ULevelComponent

GetBaseExpYield	
► Before	<pre>const float OriginalYield, float&amp;ReturnedYield</pre>
► After	const float OriginalYield, const float ReturnedYield

GetCXP	
► Before	<pre>const uint32 OriginalCXP, int32&amp;ReturnedCXP</pre>
Note:	ReturnedCXP is int32% instead of uint32% for Blueprint compatability.
► After	const uint32 OriginalCXP const int32 ReturnedCXP
Note:	ReturnedCXP is const int32 instead of const uint32 for Blueprint compatability.

Table 2: Outlets for ULevelComponent (Continued)

GetExpYield	
► Before	<pre>const float OriginalYield, float&amp;ReturnedYield, const uint16 DefeatedLevel, const uint16 VictoriousLevel</pre>
Note:	"Defeated" and "Victorious" levels are provided for flexibility (e.g., in case you want to yield exp differently based on level difference, although technically you could always back-calculate the level difference based on the equation and <code>OriginalYield</code> ).
► After	const float OriginalYied, const float ReturnedYield, const uint16 DefeatedLevel, const uint16 VictoriousLevel
Note:	"Defeated" and "Victorious" levels are provided for symmetry with respect to the <b>Before</b> delegate (since <b>ReturnedValue</b> is already calculated, I can't think of why you would need them, but you never know!).

GetMaxLeve	ol .
► Before	const uint16 DefaultMax, int32&AttemptedMax
Note:	DefaultMax is defined in the code. It should normally be 100, but may change for certain subclasses (e.g., a UBossLevelComponent may have a max of 200 instead).  AttemptedMax is int32& instead of uint16& for Blueprint compatability.
► After	const uint16 DefaultMax const int32 ReturnedMax

Table 2: Outlets for ULevelComponent (Continued)

GetMinLevel	
▶ Before	const uint16 DefaultMin, int32& AttemptedMin
Note:	DefaultMin is defined in the code. It should normally be 1, but may change for certain subclasses (e.g., a UEggLevelComponent may have a min of 0 instead for whatever reason).  AttemptedMin is int32& instead of uint16& for Blueprint compatability.
► After	const uint16 DefaultMin const int32 ReturnedMin
Note:	ReturnedCXP is const int32 instead of const uint32 for Blueprint compatability.

GetBaseExpYield	
▶ Before	<pre>const float OriginalYield, float&amp;ReturnedYield</pre>
► After	const float OriginalYield, const float ReturnedYield

SetBaseExpYield	
► Before	<pre>const float OldYield, const float InputYield, float&amp;AttemptedYield</pre>
► After	const float OldYield const float InputYield, const float NewYield
Note:	<ul> <li>▷ OldYield is the yield prior to calling SetBaseExpYield,</li> <li>▷ InputYield is the original, unmodified input to SetBaseExpYield,</li> <li>▷ AttemptedYield is the modified value that will be used to set the base exp yield.</li> </ul>

 ${\bf Table\ 2:\ {\tt Outlets}\ for\ {\tt ULevelComponent}\ (Continued)}$ 

SetCXP	
► Before	const uint32 OldCXP, const int32 InputCXP, int32& AttemptedCXP
Note:	AttemptedCXP is int32& instead of uint32& for Blueprint compatability.
► After	const uint32 OldCXP const int32 InputCXP, const uint32 NewCXP
Note:	UStatsComponent subscribes to this in order to change stats on level change.  ▷ OldCXP is the cumulatie experience points prior to calling SetCXP,  ▷ InputCXP is the original, unmodified input to SetCXP,  ▷ AttemptedCXP is the modified value that will be used to set the cumulative experience points.

Table 3: Outlets for UStatsComponent

ModifyStat	
▶ Before	<pre>const EStatEnum TargetStat, const EStatValueType ValueType, const EModificationMode Mode, const float OriginalValue, float&amp;AttemptedValue</pre>
► After	<pre>const EStatEnum TargetStat, const EStatValueType ValueType, const EModificationMode Mode, const float OriginalValue, const float NewValue</pre>
Note:	All "ModifyStat" functions from UStatsComponent (such as ModifyStatsUniformly or RandomizeStats) go through ModifyStatInternal, which calls this Outlet.

Table 3: Outlets for UStatsComponent (Continued)

RandomizeStats	
► Before	<pre>const EStatEnum TargetStat, const FStatRandParams OriginalParams, FStatRandParams&amp;ParamsToBeUsed</pre>
► After	const EStatEnum TargetStat, const FStatRandParams OriginalParams, const FStatRandParams UsedParams
Note:	The EStatEnum is not the acutal FStat. To get the FStat (such as FHealth), use UStatsComponent::GetStat(EStatEnum)

RecalculateStats	
▶ Before	<pre>const EStatEnum TargetStat, const bool bResetCurrent, const float OriginalCurrent, const float OriginalPermanent</pre>
► After	<pre>const EStatEnum TargetStat, const bool bResetCurrent, const float OriginalCurrent, const float OriginalPermanent</pre>