Summary | Properties of Materials

Introduction

Be sure to revise the second unit of Chemistry in G.C.E (A/L).

Materials

Materials can be divided into 4 sub-classifications.

- Metals
- Ceramics
- Polymers
- Composites

Materials can also be categorized based on their usage or their functionalities.

Property

A property is the response given by a material to a specific stimulus

- Mechanical properties stress
- Electrical properties electric field
- Magnetic properties magnetic field
- Optical properties electromagnetic or light radiation

Metals

Metals can be categorized into 2 types.

Pure Metals

Inter-molecular bonds: Metallic bonds. Commonly not used in the pure form.

Pure metals might be:

- not strong enough
- too weak to corrosion

Alloys

Which contain more than one metallic element.

Examples:

- Steel [Fe+C]
- Brass [Cu+Zn]
- Bronze [Cu+Sn]
- Gold jewelry (Au+Cu)
- Duralumin [Al+Cu] used for aircraft body
- Stainless steel [Fe+C+Cr+Ni],
- Cast iron [Fe+C]

Alloys have a parent metal (mostly used metal, percentage-wise) and one or more alloying elements (all elements other than parent metal).

(i) Super Alloys

Alloys containing too many alloying elements (maybe even 20).

(i) Note

Steel (Fe + C) has maximum of 2% C. Won't break easily (ductile).

Cast Iron (Fe + C) has 2%-4% C. Will break easily (brittle).

Properties

- Fe, Co, Ni, and their alloys are magnetic
- · Good electrical conductivity
- Good thermal conductivity
- · High strength
- High stiffness (= high young's modulus)
- Good ductility

(i) Note

Ductile - easily changes shape by applying force.

Brittle - easily breaks when applying force.

Ceramics

Inter-molecular bonds: covalent and/or ionic.

Properties

- Non metallic
- Inorganic
- Produced by: shaping => firing.
- High melting temperatures (some can survive upto $8000\degree$ C)
- Low density
- High strength, stiffness, hardness
- Corrosion-resistant
- Generally good insulators (electrical and thermal)
- Brittle as glass. Behaves glass-like mostly.

(i) Note

Glass is **not** an element of ceramics. Hugely differs in structure.

Some ceramic materials are:

- magnetic
- piezoelectric
- <u>superconductors</u> (only few, and only at very low temperatures)

Types

2 types:

- Traditional clay-based items like pottery, porcelain, and tiles
- Advanced like silicon carbide, boron nitride, zirconia

Examples

- Sand
- Tiles
- Cement
- Concrete

Polymers

Inter-molecular bonds: Covalent and Van der Waals or Hydrogen.

Properties

- Has a repeating structure
- lightweight
- corrosion-resistant
- · easy to process at low temperatures
- · generally inexpensive
- · generally low strength
- generally high toughness
- good heat, electrical insulators (but <u>conductive polymers</u> exist)

Examples

Plastics

- Polyvinylchloride (PVC)
- Polyethylene / Polythene (PE)
- Polypropylene (PP)
- Polystyrene (PS)
- Polypropylene used in kitchen-were
- Polymethylmethacrylite (PMMA) Perspex
 It's transparent and lightweight. Used in aircraft windows and contact lenses.
- Polytetrafluoroethylene (PTFE) Teflon

Rubber

- Polyisoprene / Natural rubber
- Styrenebutadiene rubber (SBR)

Composites

Materials that are a mixture of 2 materials. Materials are combined together to get the advantages of two materials.

Examples

- Concrete (conventional one)
- Fiber glass (GFRP)

Fiber glass is a combination of glass and plastic. Not brittle. The procedure to creating fiber glass: glass => fiber (a shape not material) => add plastic == fiber glass

Crystal Structure

Materials are categorized into 2, based on the arrangement of atoms or molecules.

- Crystalline
- Amorphous

Crystalline

When atoms or molecules are arranged in a ordered structure. Long-order is present.

- Situated in a repeating array over large atomic distances (long-range order).
- Example: Metals and Ceramics.

Atomic arrangement is usually described by **space lattice**.

Amorphous (or Non Crystalline)

When atoms or molecules are randomly arranged. Long-range order is absent.

- · Example: Glass.
- Polymers are semi-crystalline.

Space Lattice

An infinite set of equally-spaced **points** in a space.

Set of lines are used to connect these points to provide a useful guide to the eye. They are not part of the lattice.

Unit Cell

Smallest repeating parallelepiped inside the lattice. By stacking in all directions, the lattice can be generated.

Density

$$ho = rac{ ext{Mass/unit cell}}{ ext{Volume/unit cell}} = rac{1}{v}(rac{M}{L} imes n)$$

Here:

- $oldsymbol{v}$ volume of the unit cell
- ullet M molar mass
- n atoms per unit cell
- ullet avagadro's number

Crystalline systems

• All crystalline materials fall within one of the 7 possible shapes and 4 variants.

The shapes

Don't have to memorize.

- Cubic
- Hexagonal
- Tetragonal
- Rhombohedral (Trigonal)
- Orthorrhombic
- Monoclinic
- Triclinic

The variants

- Simple: atoms at the corners only.
- Base-centered: atoms at the corners and center of 2 opposing sides only.
- Body-centered: atoms at the corners and center only.
- Face-centered: atoms at the corners and center of all faces only.

Bravais showed that only **14** of 28 (7 shapes x 4 variants) are possible in real life.

Only 4 of them are studied in s1.

- Simple cubic (sc)
- Body-centered cubic (bcc)
- Face-centered cubic (fcc)
- Hexagonal close packed or Close packed hexagonal (hcp/cph)

Coordination number

Coordination number of a lattice system is the number of particles that each particle contacts.

Atomic Packing Factor (APF)

$$ext{APF} = rac{ ext{True volume}}{ ext{Bulk volume}} = rac{ ext{Volume of atoms/unit cell}}{ ext{Volume/unit cell}}$$

Geometrically maximum APF in real life (assuming spherical atoms) is 74%. If a structure has 74% APF, the structure is called a **close-packed structure**.

Interstitial sites (aka holes, voids)

Empty space that exists between the packing of atoms in a crystal structure.

Octahedral interstices

Locations of void spaces available in an FCC. Located at the center of each edge and body-center of the unit cell.

Summary of the 4

	sc	bcc	fcc	hcp
Unit cell	a	a	a	a
Constants	a	a	a	a,c (where $c>a$)
With atom radius	a=2r	$a=rac{4}{\sqrt{3}}r$	$a=rac{4}{\sqrt{2}}r$	$a=2r; c=\sqrt{rac{8}{3}}a$
Volume	a^3	a^3	a^3	$rac{3}{2}\sqrt{3}a^2c$

	sc	bcc	fcc	hcp
Atoms per unit cell	1	2	4	6
Composition	$8 \cdot \frac{1}{8}$	$8 \cdot \frac{1}{8} + 1$	$8 \cdot \frac{1}{8} + 6 \cdot \frac{1}{2}$	$3+12\cdot \tfrac{1}{6}+2\cdot \tfrac{1}{2}$
Coordination number	6	8	12	12
APF	52.36%	68%	74%	74%
Examples	Po	Fe, Cr, W	Al, Cu, Ni	Mg, Zn

The unit cell images are taken from Wikipedia.


• Simple cubic: Original file @ Wikipedia

• Body-centered cubic: Original file

• Face-centered cubic: Original file

Hexagonal close-packed: By <u>Original: Dornelf</u> Vector: <u>DePiep</u> - Own work based on: <u>Hexagonal</u> <u>close packed.png</u>, <u>CC BY-SA 3.0</u>, <u>Link</u>

Miller Indices



Any vertex can be chosen as the origin.

Notation

- · Minus noted with a bar
- Addition and subtraction is carried out like vectors
- (1,1,0) Atom/Vertex
- [110] Direction, no commas
- ullet <110> Family of directions
- (100) Plane, no commas
- $\{100\}$ Family of planes
- Always will be whole numbers. Fractions must be multiplied by LCM.

Direction

Equivalent directions are grouped into a family.

Direction families

<100>

- No of planes: 6
- $[100], [010], [001], [\bar{1}00], [0\bar{1}0], [00\bar{1}]$

<110>

- No of planes: 12
- $[011], [01\overline{1}], [0\overline{1}1], [0\overline{1}\overline{1}], [101], [10\overline{1}], [\overline{1}01], [\overline{1}0\overline{1}], [110], [1\overline{1}0], [\overline{1}10], [\overline{1}\overline{1}0]$

<111>

- No of planes: 8
- [111], [111], [111], [111], [111], [111], [111], [111]

Show the direction

To show the direction [132], for example:

Take the point (1,3,2). Divide by the highest number (3, in this case) to bring the point inside the unit cell. The resulting point will be $(\frac{1}{3},1,\frac{2}{3})$. The direction is given by vector from (0,0,0) to the resulting point.

Close packed direction

All neighbour atoms in a direction touch each other. For example: (110) of fcc.

Plane

Steps

- · If sitting on any axes, move the origin.
- Find the reciprocals.

Plane families

100

- Denotes as $\{100\}$
- No of planes: 6
- $(100), (010), (001), (\bar{1}00), (0\bar{1}0), (00\bar{1})$

110

- Denotes as $\{110\}$
- No of planes: 12
- $(011), (01\overline{1}), (0\overline{1}1), (0\overline{1}\overline{1}), (101), (10\overline{1}), (\overline{1}01), (\overline{1}0\overline{1}), (110), (1\overline{1}0), (\overline{1}10), (\overline{1}10)$

111

- Denotes as **{111}**
- No of planes: 8
- $(111), (11\overline{1}), (1\overline{1}1), (\overline{1}11), (\overline{1}\overline{1}1), (\overline{1}1\overline{1}), (1\overline{1}\overline{1}), (\overline{1}\overline{1}\overline{1})$

The above are the common planes. There are other planes as well.

Show the plane

- Divide by the smallest non-zero number.

Close packed plane

All neighbour atoms in a crystal plane touch each other. For example: (111) of fcc.

Planar Density / Aerial Density

Number of atoms in a unit area in a specific plane. Differs between different planes in a single crystal structure.

Allotropy

Ability of a single substance to exist in more than one physical form.

Examples:

- Fe
- C
- o Graphite
- Diamond
- Buckminsterfullerene
- Carbon nanotubes
- Graphene

Defects in Crystals

There won't be a crystal with 100% of perfect arrangement. Defects are are advantages in materials most of the time.

- 1. Point defects
- 2. Line defects / Dislocations
- 3. Planar defects
- 4. Bulk defects Related to volumetric defects. Common for any materials. Example: crack, holes. Not covered in s1.

Point defects

Related to a single atom.

- Vacancy Missing parent atom
- · Self-interstitial atom A parent atom entered into an interstitial site
- Interstitial impurity atom A foreign atom entered into an interstitial site
- Substitutional impurity atom A foreign atom replaced a parent atom or a vacancy

Line defects

Related to a line of atoms. Three types:

- Edge dislocation only covered in s1
- Screw dislocation
- Mixed dislocation (combination of above 2)

Edge dislocation

Caused by removal of a half plane.

Half plane

TODO

Slip plane

Plane that is perpendicular to the half plane.

Dislocation line

Intersecting line of half plane and slip plane.

Planar defects

Related to a plane of atoms.

Solidification

The process of conversion liquid to solid. Occurs in 3 steps:

- Nucleation
- Growth of crystals
- Formation of grain structure

Tiny solid particles forms. Called as Nuclei (nothing related to atom's nucleus). Each nucleus grows bigger and forms a crystal. And then forms grains.

Grain

A group of atoms packed in a particular orientation that is different from that of the neighbor ones.

Each grain is usually in micrometer in size. Grain structure can only be observed through a microscope after careful preparation of samples (microstructure).

Grain boundaries

Boundary between 2 adjacent grains is grain boundary.

Planar defects found in crystalline materials.

Functional Materials

Classification of materials based on whether most important function they perform is either mechanical, structural, biological, electronic, magnetic, or optical.

These materials have one or more properties that can be significantly changed in a controlled fashion with an external stimuli.

List of properties

- Electrical properties
 - Piezoelectricity
 - Ferroelectricity
 - Superconductivity
 - Capacitance
- Optical properties
 - Photoluminescence
 - Photochromism
 - Fluorescence
 - Photoelectricity
- Magnetic Properties
 - Diamagnetism
 - Ferromagnatism
 - Ferrimagnetism
 - Paramagnetism
 - Anti-ferri magnetism
- Chemical Properties / Reactivity properties
 - reactivity with other substances
 - catalytic properties

This PDF is saved from https://s1.sahithyan.dev