# Java StringBuffer class

Java StringBuffer class is used to created mutable (modifiable) string. The StringBuffer class in java is same as String class except it is mutable i.e. it can be changed.

Note: Java StringBuffer class is thread-safe i.e. multiple threads cannot access it simultaneously. So it is safe and will result in an order.

## Important Constructors of StringBuffer class

- 1. **StringBuffer():** creates an empty string buffer with the initial capacity of 16.
- 2. **StringBuffer(String str):** creates a string buffer with the specified string.
- 3. **StringBuffer(int capacity):** creates an empty string buffer with the specified capacity as length.

## Important methods of StringBuffer class

- public synchronized StringBuffer append(String s): is used to append
  the specified string with this string. The append() method is overloaded
  like append(char), append(boolean), append(int), append(float),
  append(double) etc.
- 2. **public synchronized StringBuffer insert(int offset, String s):** is used to insert the specified string with this string at the specified position. The insert() method is overloaded like insert(int, char), insert(int, boolean), insert(int, int), insert(int, float), insert(int, double) etc.
- 3. public synchronized StringBuffer replace(int startIndex, int endIndex, String str): is used to replace the string from specified startIndex and endIndex.

- public synchronized StringBuffer delete(int startIndex, int endIndex): is used to delete the string from specified startIndex and endIndex.
- 5. **public synchronized StringBuffer reverse():** is used to reverse the string.
- 6. **public int capacity():** is used to return the current capacity.
- 7. **public void ensureCapacity(int minimumCapacity):** is used to ensure the capacity at least equal to the given minimum.
- 8. **public char charAt(int index):** is used to return the character at the specified position.
- 9. **public int length():** is used to return the length of the string i.e. total number of characters.
- 10. **public String substring(int beginIndex):** is used to return the substring from the specified beginIndex.
- 11. **public String substring(int beginIndex, int endIndex):** is used to return the substring from the specified beginIndex and endIndex.

## What is mutable string

A string that can be modified or changed is known as mutable string. StringBuffer and StringBuilder classes are used for creating mutable string.

#### 1) StringBuffer append() method

The append() method concatenates the given argument with this string.

```
class A{
  public static void main(String args[]){
  StringBuffer sb=new StringBuffer("Hello ");
  sb.append("Java");//now original string is changed
  System.out.println(sb);//prints Hello Java
  }
}
```

#### 2) StringBuffer insert() method

The insert() method inserts the given string with this string at the given position.

```
class A{
public static void main(String args[]){
StringBuffer sb=new StringBuffer("Hello ");
sb.insert(1,"Java");//now original string is changed
System.out.println(sb);//prints HJavaello
}
}
```

#### 3) StringBuffer replace() method

The replace() method replaces the given string from the specified beginIndex and endIndex.

```
class A{
  public static void main(String args[]){
  StringBuffer sb=new StringBuffer("Hello");
  sb.replace(1,3,"Java");
  System.out.println(sb);//prints HJavalo
  }
}
```

#### 4) StringBuffer delete() method

The delete() method of StringBuffer class deletes the string from the specified beginIndex to endIndex.

```
class A{
public static void main(String args[]){
StringBuffer sb=new StringBuffer("Hello");
sb.delete(1,3);
System.out.println(sb);//prints Hlo
}
}
```

#### 5) StringBuffer reverse() method

The reverse() method of StringBuilder class reverses the current string.

```
class A{
public static void main(String args[]){
  StringBuffer sb=new StringBuffer("Hello");
  sb.reverse();
  System.out.println(sb);//prints olleH
}
}
```

#### 6) StringBuffer capacity() method

The capacity() method of StringBuffer class returns the current capacity of the buffer. The default capacity of the buffer is 16. If the number of character increases from its current capacity, it increases the capacity by (oldcapacity\*2)+2. For example if your current capacity is 16, it will be (16\*2)+2=34.

```
class A{
public static void main(String args[]){
StringBuffer sb=new StringBuffer();
System.out.println(sb.capacity());//default 16
sb.append("Hello");
System.out.println(sb.capacity());//now 16
sb.append("java is my favourite language");
```

```
System.out.println(sb.capacity());//now (16*2)+2=34 i.e (oldcapacity*2)+2
}
}
```

#### 7) StringBuffer ensureCapacity() method

The ensureCapacity() method of StringBuffer class ensures that the given capacity is the minimum to the current capacity. If it is greater than the current capacity, it increases the capacity by (oldcapacity\*2)+2. For example if your current capacity is 16, it will be (16\*2)+2=34.

```
class A{
  public static void main(String args[]){
  StringBuffer sb=new StringBuffer();
  System.out.println(sb.capacity());//default 16
  sb.append("Hello");
  System.out.println(sb.capacity());//now 16
  sb.append("java is my favourite language");
  System.out.println(sb.capacity());//now (16*2)+2=34 i.e (oldcapacity*2)+2
  sb.ensureCapacity(10);//now no change
  System.out.println(sb.capacity());//now 34
  sb.ensureCapacity(50);//now (34*2)+2
  System.out.println(sb.capacity());//now 70
  }
}
```



## Share this page



#### **Latest 4 Tutorials**



CouchDB



Docker





RichFaces