Unreal Engine 5 - Lesson 8&9 - AI

Nicolas Serf - Gameplay Programmer - Wolcen Studio serf.nicolas@gmail.com


Summary

- Navigation Systems
 - o Basics
 - o Modifier Volume
 - o Link Proxies
 - o Generating
 - Custom Navigation Area & Queries
 - o Avoidance
 - RVO
 - DCM
- Smart Objects
 - o Overview
 - o Searching
 - Claiming
 - o Approaching
 - Releasing
- Behavior Trees
 - Biggest differences
 - Node instancing
 - o Nodes
- Environment Query System
- AIPerception



Navigation System - Basics


- To make it possible to find a path between a start location and a destination, a Navigation Mesh is generated from the world's collision geometry. This simplified polygon mesh represents the navigable space in the Level. Default settings subdivide the Navigation Mesh into tiles to allow rebuilding localized parts of the Navigation Mesh.
- The resulting mesh is made of polygons and a cost is associated with each polygon. While searching for a path, the pathfinding algorithm will attempt to find an optimal path with the lowest cost to the destination.
- In order to generate a NavMesh, it is mandatory that you add a specific actor into your level which is called NavMeshBoundsVolume.
- With the NavMeshBoundsVolume selected, go to the Details panel and scale the
 volume to a value that ensure to contains every mesh that needs to be taken into
 consideration will baking the Navmesh.
- In order to visualize the generated Nav Mesh, you can press P key
- You may have some issue regarding the NavMesh, with some artifacts on elevation. It is due to Draw Offset value which is located on the actor RecastNavMesh-Default. On the detail panel of that actor, you can adjusts the height offset where the Navigation Mesh is drawn for better readability.
- From RecastNavMesh-Default, you can modify various display options like
 - Draw Poly Edges
 - o Draw Tile Bounds
 - Generally speaking, you can modify how it is **generated** in the **Generation section**






Navigation System - Navigation Modifier Volume


- If you would like to modifying the generate NavMesh, the 1st most obvious is to add some actors inside the level with a collision on them
 - This simple operation will make the **NavMesh** to include this actor as **interfering** with the NavMesh and therefore creating an **obstacle** in it
- Another solution is to works with **Navigation Modifier Volume**.
- It is an actor that you can find from the actor finder
- This can be used to change the **properties** of the **polygons** within the volume space to modify their **traversal cost**
- The polygon properties are defined by the appropriate Area Class of the Navigation Modifier Volume. This class determines the effect on the Navigation Mesh. You can use the built-in classes to modify the mesh or create your custom implementations.
- As you can see, by default there is some default UObject classes for the Area Class
 - NavArea_Default: Assigns the same navigation cost to the area inside the volume and the Navigation Mesh by default.
 - NavArea_LowHeight: The Navigation Mesh will not generate navigation data inside this volume.
 - NavArea_Null: The Navigation Mesh will not generate navigation data inside this volume.
 - NavArea_Obstacle: Assigns a high navigation cost to the area inside the volume.
- Based on the cost of this Area Class and the global cost of the path, your agent will try to avoid way more paths that includes more costly areas






Navigation System - Navigation Link Proxies

- Navigation Link Proxies connect two areas of the Navigation Mesh that don't
 have a direct navigation path. While a path is being searched, Navigation Link
 Proxies are used as extra connections that Agents can use to reach their
 destination.
- Navigation Link Proxies are commonly used to build bridges between areas with separate Navigation Meshes and to instruct Agents that they can fall or jump from a platform towards their goal when there is no continuous navigation path available.
- A NavLinkProxy is an actor to place in the world
- With the Nav Link Proxy selected, click the PointLinks[0].Left handle and move it so it's placed on one side of the mesh. Click the PointLinks[0].Right handle and move it so it's placed on the opposite side of the mesh. This is how you define the bridge
- With the Nav Link Proxy selected, go to the Details panel and expand the section labeled 0 under Point Links to find the Direction dropdown. You can choose to have the Direction be Both Ways, Left to Right, or Right to Left






Navigation System - Smart Link


- In this section, you will learn how to use a Smart Link on a Nav Link Proxy to allow your Agent to jump from one platform to another.
- Create a BP class which inherit from NavLinkProxy
- In the event graph, you can listen to an event called ReceiveSmartLinkReached
- From within this event, you can create a graph as complex as you want in order to compute correctly how you can this link to behave on the actor that is crossing it
- There is a useful when it comes to computation of velocity while jumping from an edge which is SuggestProjectileVelocityCustomArc
- Do not forget to click the button Copy End Points from Simple Link to Smart Link and tick the correct options






Navigation System - Generating Nav Mesh

- Unreal Engine comes with three Navigation Mesh generation modes
 - o Static
 - The Navigation Mesh is **generated offline** and is **saved** with the **Level**. The Navigation Mesh is **loaded** at **runtime** and **cannot change**.
 - o Dynamic
 - The Navigation Mesh is generated offline and is saved with the Level or built at runtime. At runtime, the navigation-relevant data used by the Navigation Mesh can be updated and the generation is performed on the tiles affected by the change in the data.
 - o Dynamic Modifiers Only
 - The Navigation Mesh is generated offline and is saved with the Level. At runtime, only Navigation Modifiers such as Navigation Areas, Navigation Links, and dynamic objects, can modify the existing Navigation Mesh by changing the cost or block areas. No new Navigation Mesh surfaces are generated at runtime.
 - This method allows the Navigation Mesh to cache collision data and can result in up to 50% cheaper processing of the affected tiles.
 - Advanced users should use this mode after careful consideration of its benefits and limitations.
- By default, the Navigation Mesh is configured to be Static. However, you can set your
 Navigation Mesh generation to one of the dynamic modes so it can change at runtime.




Navigation System - Generating Nav Mesh - Runtime Generation

- In order to modify the generation setting, go into Project Settings,
 Navigation Mesh under Runtime section and in runtime generation dropdown, select the option you need
- In order to have a dynamic modifier, you need to add an component which is called NavModifier.
- It is important to say once again that no new Navigation Mesh is being generated in the Level. The Navigation Modifier is simply changing the existing Navigation Mesh.
- Following the same idea, you can select Dynamic as Runtime Generation
- In this situation, it will be easier to setup the navmesh to update dynamically, but it will be way more costly than Dynamic Modifiers Only




Navigation System - Custom Navigation Areas and Query Filters


- The Agent determines the **most optimal route** to its destination by comparing the **cost** of each navigation **polygon** within the Navigation Mesh. If all polygons along the route are of equal cost, then the Agent will choose the **shortest path** to its target (usually a straight line).
- You can influence the cost of the navigation polygons using Navigation Modifier Volumes and Navigation Query Filters.
- Navigation Modifier Volumes use Area Classes to determine the Default Cost multiplier of navigation within the volume. Area Classes also define the Fixed Area Entering Cost, which is the initial cost applied when the Agent enters the area. You can create as many Area Classes as needed to influence how your Agents navigate your Level.
- Navigation Query Filters contains information about one or more Area Classes and can override the cost values if needed. You can create as many Query Filters as needed to further customize how your Agents navigate your Level.



Navigation System - Custom Navigation Areas and Query Filters

- Obviously, in order to **create** a new area class, you'll need to create blueprint / c++ class which in inheriting from **NavArea**
- You can modify debug color which will be easier for level designer to visualize how they are setting the map
- You can then modify **actual cost** which will not be visible by level designer but is used for **computation**








Navigation System - Custom Navigation Areas and Query Filters

- To create a new navigation query filter, you need to create a blueprint / c++ class which inherit from NavigationQueryFilter
- From within the detail panel, you have access to an **array** which will allow you this **query filter** to specifier how it should **interact** with **specific Area class**
 - Area Class: The class which we talk just previously
 - Travel cost override: Ignore the default cost parametrize in the area class if ticked and take this value instead
 - Entering cost override: Ignore the default entering cost parametrize in the area class if ticked and take this value instead
- When you are calling MoveToActor which comes from AIController, you have an option to specific the Filter class that needs to be used during the computation



Navigation System - Using Avoidance


- While pathfinding can determine a path around objects that don't move, avoidance algorithms are better suited to handle moving obstacles.
- There are two methods of avoidance the Agents can use to navigate around dynamic obstacles and each other
 - o Reciprocal Velocity Obstacles (RVO)
 - The RVO system calculates the velocity vectors for each Agent to avoid a collision with nearby Agents. This system looks at the nearby Agents and assumes they are traveling with a constant velocity within each time step of the calculation. The optimal velocity vector chosen is the closest match to the Agent's preferred velocity in the direction of its target.
 - Unreal Engine's implementation of RVO includes optimizations to reduce frame rate dependencies. It also includes improvements to avoid constant path recalculation and a priority system to help resolve potential collisions. RVO does not use the Navigation Mesh for avoidance, so it can be used separately from the Navigation System for any Character. It is included in the Character Movement component of the Character class.
 - Detour Crowd Manager (DCM)
 - The DCM system handles avoidance between Agents by using an adaptive RVO sampling calculation. It does this by calculating a coarse sample of velocities with a bias toward the Agent's direction that allows for a significant improvement in the quality of the avoidance over the traditional RVO method. This system also uses visibility and topology path corridor optimizations to further improve collision avoidance.
 - The Detour Crowd Manager system is highly configurable with options to specify sampling patterns, the maximum number of Agents, and Agent Radius. The system is included in the DetourCrowd AI Controller class and can be used with any Pawn class.

Method	Description	Limitation
RVO	 Agents avoid obstacles by using velocity vectors within a specified radius. Included in the Character Movement component of the Character class. 	 Less configurable compared to the Detour Crowd Manager. Limited to the Character class. Does not use the Navigation Mesh for avoidance so Agents can potentially go "out of bounds".
DCM	 Agents avoid obstacles by using path optimizations along with velocity vectors within a specified radius. Included in the DetourCrowd Al Controller class. Has a fixed maximum number of Agents defined in the project settings. 	Has a fixed maximum number of Agents defined in the project settings.

Navigation System - Using Avoidance - RVO

- Given RVO is located on the character movement component, 1st step is obviously to add a Character Movement Component into the actor that needs to have avoidance through RVO
- In the details we can configure if we want to use the avoidance and some parameters
 - UseRVOAvoidance : Should RVO algorithm be used
 - AvoidanceConsiderationRadius: RVO algorithm only consider obstacles that fall into this radius. It is an important parameter to tweak
 - Avoidance Weight: How heavy RVO algorithm needs to intervene.
 0.5 is default value which works in most cases
 - Avoidance UID: Automatically generated and important for interacting with AvoidanceManager in C++
 - Avoidance Group: Which group this character belongs to
 - o GroupsToAvoid: Which group this character should avoid
 - GroupsToIgnore: Which group this character should ignore
- In the standard version it is as easy as that
- Obviously, given everything is open in Unreal, if you want to override how RVO works, you could decide to override the CharacterMovementComponent but it is a big chunk






Navigation System - Using Avoidance - Advanced RVO

- If you have a reference to the CharacterMovement, from blueprint you'll see that you can read all the variables and parameters we talked the slide before.
- From Blueprint, we can't sadly modify this values.
- However, we can still modify **slightly** the behavior of **RVO**. We have access to
 - Enabling RVO algorithm
 - Set the avoidance group
 - Set the group to avoid
- From C++, you have a new functionalities from which you'll be able to modify the RVO.
 - 1st, you have access to UAvoidanceManager, which stores data of all agent that use RVO
 - Thanks to AvoidanceUID, you can query the Avoidance Manager to get FNav AvoidanceData struct which hold specific avoidance data of the character.
 - You could for example have access to the current velocity avoidance through GetAvoidanceVelocity()








Navigation System - Using Avoidance - Advanced RVO


- It important to understand that RVO do not take into account the NavMesh, which could mean that the agent get pushed out of the navmesh.
 - Even if it is quite minor, it is something that you need to take into account
 - You could choose to have check while moving to ensure that you stick into the NavMesh
 - You could choose to have wall boundaries into your levels to ensure that the movement out of the navmesh is not possible
 - o etc...
- If you want RVO to works on non-character actor, you'll either needs to recreate RVO algorithm, or adapt your actor to uses the CharacterMovementComponent
- RVO do not works very well when there is a large number of agent in a confined space
- RVO is really **fast**
- Finally, if you want more detail about the avoidance RVO... Check the source code at

Runtime/Engine/Classes/AI/Navigation/AvoidanceManager.h



Navigation System - Using Avoidance - DCM

- Within a world there is always an object called DetourCrownManager.
 - It is a singleton
 - It is responsible for **coordinating crowds** in the game
 - An actor needs to be registered into the DetourCrownManager to be considered by the system
 - The DetourCrownManager accepts anything that implements the ICrowdAgentInterface, which provides data to the Manager
- Even if you could create an actor which implement the interface, Unreal provides a special component called UCrowdFollowingComponent which implement the interface
 - It makes directly the agent registered for the DetourCrownManager
 - o It activate by default the **Detour Behavior**
- To make things easier, Unreal provides a special controller called
 DetourCrownAIController which you can select in the dropdown of the pawn
- Obviously, you need to inherit from this special controller in either blueprint or c++





Navigation System - Using Avoidance - DCM

• Note that UCrowdFollowingComponent implement the ICrowdAgentInterface which internally uses the avoidance settings located in the

CharacterMovementComponent


- Therefore, the settings for **RVO** are still **impacting** the **DCM**
- Weight will not be used
- Notice that you should not activate RVO & DCM at the same time except if you know what you are doing
- From this point, you can go into **Project Settings** and navigate in **Crow Manager** section to **parametrize** furthermore the DCM
 - In this section, you can adjust several settings for the Detour Crowd Manager system, such as the Max Agents used by the system and the Max Agent Radius used for the avoidance calculation.
 - There is 4 avoidance config which correspond to quality: Low, Medium, Good, High
 - The quality value is set in UCrowdFollowingComponent with the Avoidance Quality





Navigation System - Using Avoidance - DCM

- In order to fully understand the settings in avoidance config, it would require to understand how the algorithm works
- Let's make a simplified version just to get the idea, you can always document yourself for more details
- Algorithm does a sampling by creating a set of rings (Adaptative Rings) around
 the center point (where the agent is) with a bias (Velocity Bias) in the direction of
 the velocity
- Each ring is sampled (divided) by **Adaptative Divisions**
- Then the algorithm recursively **refines** the search by using a **smaller set** of **rings** which are **centered** on the best sample of the **previous iteration**
- The algorithm repeat this process Adaptative Depth times
- During each iteration, the best sample is considering the following
 - Does the direction of the agent match the current velocity?
 The weight is Desired Velocity Weight
 - Does the agent goes sideway?
 The weight is SideBiasWeight
 - Does the agent collides with any known obstacles?
 The weight is ImpactTimeWeight
 It scans a range by considering the current velocity within ImpactTimeRange parameter



Velocity Bias	0,5
Desired Velocity Weight	2,0
Current Velocity Weight	0,75
Side Bias Weight	0,75
Impact Time Weight	2,5
Impact Time Range	2,5
Custom Pattern Idx	255
Adaptive Divisions	5
Adaptive Rings	2
Adaptive Depth	1

Smart Objects - Overview

- Smart Objects are **objects placed** in a level that **AI Agents** and **Players** can **interact** with. These objects contain all the information needed for those interactions.
- Smart Objects are part of a global database and use a spatial partitioning structure. This means that they can be queried at runtime by using filters such as location, proximity to the Agent, and tags.
- At a high level, Smart Objects represent a set of activities in the level that can be used through a reservation system. It's important to note that Smart Objects do not contain execution logic. Instead, they provide all necessary information to the interactor to be able to perform the interaction, depending on its implementation. Each interactor (Agent or Player) does its own implementation logic for a Smart Object.

• SmartObject Subsystem

• The SmartObject subsystem is responsible for keeping track of all Smart Objects available in the level. This is the link between the Smart Object components and the collection. This subsystem is automatically created in the level when the Smart Objects plugin is active, and will create the Smart Object collection if it's missing.

• SmartObject Collection

- The SmartObject Collection contains a list of all SmartObject components associated with the level. The collection works with persistent levels and must be built manually by the user.
- This means that Smart Objects registered with a collection are kept alive, regardless of whether the Smart Object components are loaded or unloaded from the persistent level.



Smart Objects - Overview

• SmartObject Component

- The SmartObject component can be added to any Actor to mark it as a Smart Object in the level. The component points to a Smart Object Definition asset, which stores the configuration of a given Smart Object template.
- The Actor containing the SmartObject component may be loaded and unloaded at runtime using Streaming. If the SmartObject component is included in the persistent world's Smart Object collection, a runtime instance will remain active in memory and will be considered as part of the simulation. If the Actor containing the SmartObject component is spawned at runtime, then it will not remain active in memory once it's unloaded.

• Smart Object Definition

- A Smart Object Definition is a data asset that contains the immutable data shared between multiple Smart Object runtime instances. A Smart Object Definition stores filtering information such as user-required tags, Activity tags, Object Activation tags, and the default set of Behavior Definitions that could be used to interact with the Smart Object.
- A Smart Object Definition exposes one or more Slots that can be used by Agents or Players for the specific Smart Object. Each Slot includes the location and rotation relative to the parent anchor (baked from editor placement), as well as several overridable properties. Common examples of overridable properties include user-required tags and specific Behavior Definition per Slot.

• Smart Object Behaviors Definition

- Smart Object Behaviors Definitions contain the data needed by the Agent or Player for a given interaction. The following types of Behaviors Definitions are currently available:
 - Mass Entity Behavior contains data used to configure Smart Objects that can be used by Mass Entities.
 - Gameplay Behavior contains data used to configure Smart Objects that can be used by the Gameplay Behavior plugin.



Smart Objects - Flow - Searching

• Agent Data


o In order to search for Smart Objects, the Agent needs to have one or more user tags, and a list of object tags. This information will be used when searching for matching Smart Objects in the level.

• Smart Object Data

- Smart Objects contain **one** or **more object tags** that are used to **describe** the object. They also contain a list of **user tags**, and a **tag query**. The tag query is an **expression** used to determine if the user requesting the use of the Smart Object is **allowed** to interact with it.
- Smart Objects have a Behavior Class which contains the Behavior Definition that will be used by the user once they are interacting with the Smart Object.

• Searching for a Smart Object


- 1. The Agent searches for nearby Smart Objects on a specified interval. The Agent performs the search by calling the FindSmartObjects method in the Smart Object subsystem. This method contains the user tags, object tags, Behavior Class, and search area.
- 2. The Smart Object subsystem finds all Smart Objects within the search area that match the object tags.
- 3. Each Smart Object runs its tag query using the user tags to see if there is a match and sends the results to the Smart Object subsystem.
- 4. The Smart Object subsystem returns the **Smart Object Results** to the **Agent**. The Smart Object Results are a **Struct array** containing all matching Smart Object IDs and their **free Slots**.





Smart Objects - Flow - Claiming


- 1. The Agent selects a desired Smart Object Result and calls the ClaimSmartObject method in the Smart Object subsystem. This method will attempt to claim an available Slot from the Smart Object.
- 2. The Smart Object subsystem attempts to claim an available Slot from the Smart Object.
- 3. An available Slot is claimed in the Smart Object and its state is set to Claimed. Confirmation is sent to the Smart Object subsystem.
- 4. Smart Object subsystem returns a Claim Handle to the Agent.
- 5. The Agent checks if the Claim Handle is valid. If it is valid, the claim attempt was successful and it can proceed to the next step. However, if the Claim Handle is invalid, the Agent may attempt to claim another Smart Object from the Smart Object Results.
- The claimed Slot may not be claimed by another Agent until it is released by the current Agent occupying the Slot.





Smart Objects - Flow - Approaching

- 1. The Agent calls the GetSlotLocation or GetSlotTransform method in the Smart Object subsystem and passes the Claim Handle. This method returns the location or transform of the claimed Slot.
- 2. The Smart Object subsystem returns the location or transform of the claimed Slot to the Agent.
- 3. The Agent can now start navigating to the Slot location in the Level. The Agent can use any desired navigation method to reach its destination.
- 4. The Agent arrives at the Slot location and calls the UseSlot method in the Smart Object subsystem and passes the Claim Handle.
- 5. The Smart Object subsystem returns the **Behavior Definition** struct to the **Agent**. The Behavior Definition contains all the **required data** for the Agent to **perform** its desired behavior at the **Slot location**.
- 6. The UseSlot method triggers a state change for the claimed Slot. The Slot's state is changed from Claimed to Occupied.





Smart Objects - Flow - Releasing

- 1. The Agent performs the desired behavior described in the Behavior Definition.
- 2. Once the behavior is completed or aborted, the Agent calls the ReleaseSmartObject method with the Claim Handle in the Smart Object subsystem.
- 3. The Smart Object Subsystem changes the Slot state from Occupied to Free.
- 4. The is free for another Smart Object. Agent now to perform another behavior search or
- Agents are responsible for releasing their claimed Slots. This can happen once their behavior is completed or interrupted.




Smart Objects - Flow - Aborting


- The process described above can be **interrupted** or **aborted** by the **Agent** or the **Smart Object** at any time.
- If the Smart Object's **state changes** it will automatically **release** all **Claimed** or **Occupied Slots** and will notify the corresponding Agents through the **OnSlotInvalidatedDelegate** callback. A common example is the Smart Object being **destroyed** during gameplay.
- The Agent can also abort the process at any time for any reason. In this scenario, the Agent is responsible for **releasing** the **Slot** so other **Agents** can claim it. Common examples include the Agent **dying** or performing **another task** with a **higher** priority.



Behavior Trees - Basics

- Behavior Trees are created in a visually like Blueprint in node based that have some functionality attached to them to a Behavior Tree Graph. While a Behavior Tree executes logic, a separate asset called a Blackboard is used to store information (called Blackboard Keys) the Behavior Tree needs to know about to make informed decisions.
- A typical workflow would be to create a Blackboard, add some Blackboard Keys, then create a Behavior Tree that uses the Blackboard asset (pictured below, a Blackboard is assigned to a Behavior Tree).
- In the Behavior Tree detail panel, you can select which blackboard asset needs to be assigned to it
- Behavior Trees in Unreal Engine execute their logic from left-to-right, and top-to-bottom. The numerical order of operation can be viewed in the upper-right corner of nodes placed in the graph.
- On the image we can see, a blue node is referenced as a Decorator, also known as Conditional in other Behavior Tree system
- Once you have created your Behavior Tree and logic, you will need to **run** the **Behavior Tree** during **gameplay**. Usually, you will have a **Pawn** and that Pawn will have an **associated AI Controller** which will be used to take control of and direct the **Pawn** in **performing actions**. Below, we have assigned a custom AI Controller class to our Pawn.









Behavior Trees - Biggest differences - Event Driven

- One of the ways Unreal Engine Behavior Trees differ from other Behavior Tree systems is that Unreal Engine Behavior Trees are event-driven to avoid doing unnecessary work every frame. Instead of constantly checking whether any relevant change has occurred, the Behavior Tree passively listens for "events" that can be used to trigger changes in the tree.
- Having an event-driven architecture grants improvements to both performance and debugging.
- Performance-wise, there is not much explanation to give in order to understand why it is a great difference
 - You do not waste loop cycle to iterate over a tick function checking booleans etc...
- Debugging-wise, in you are iterating over useless loops, useless values which dictated how the behavior tree should direct the calls, it may become way more complicated to easily identify what you need to look at




Behavior Trees - Biggest differences - Conditionals

- In the standard model for Behavior Trees, conditionals are Task leaf nodes, which simply do not do anything other than succeed or fail.
- Although nothing prevents you from making traditional conditional tasks, it is highly recommended that you use **Decorators** for conditionals instead.
- Making conditionals Decorators rather than Tasks has a couple of significant advantages:
 - Conditional Decorators make the Behavior Tree UI more intuitive and easier to read.
 - Since all **leaves** are action **Tasks**, it is easier to see what **actual actions** are being ordered by the tree.
- Since **conditionals** are at the root of the **sub-tree** they are **controlling**, you can immediately see what part of the tree is "closed off" if the conditionals are not met.
- In the section of a Behavior Tree screen, the **Decorators Close Enough** and **Blackboard** can prevent the **execution** of the **Sequence** node's children. Another advantage of conditional Decorators is that it is **easy** to make those **Decorators** act as **observers** (waiting for events) at critical nodes in the tree. This feature is critical to gaining full advantage from the event-driven nature of the trees.



Behavior Trees - Biggest differences - Concurrent Behaviors

- Standard Behavior trees often use a **parallel composite node** to handle concurrent behaviors and the **parallel node** begins execution on all of its **children simultaneously**. Special rules determine how to act if one or more of those child trees finish (depending on the desired behavior).
 - Parallel nodes are not necessarily multi-threading (executing tasks at the same time).
 They are just a way to conceptually perform several tasks at once. Often they still run on the same thread and begin in some sequence.
- Instead of complex parallel nodes, Unreal Engine Behavior Trees use Simple Parallel nodes, a special node type called Services, and the property Observer Aborts on Decorators to accomplish the same sorts of behaviors.
- Simple Parallel nodes have only two children
 - One which must be a **single Task node** (with **optional Decorators**), and the other of which can be a **complete sub-tree**. Think of the Simple Parallel node as "While doing A, do B as well." For example, "While attacking the enemy, move toward the enemy." A is a **primary task**, and B is a **secondary** or filler task while waiting for A to complete.
- While there are some options as to how to handle the **secondary task** (Task B), the node is **relatively simple** in concept compared to traditional parallel nodes. Nonetheless, it supports much of the **most common usage** of **parallel nodes**. Simple Parallel nodes allow easy usage of our **event-driven optimizations** while full parallel nodes would be **much more complex to optimize**.



Behavior Trees - Nodes Instancing

• Behavior Tree Nodes (referred to here as "nodes") exist as shared objects, meaning that all agents using the same Behavior Tree will share a single set of node instances. This improves CPU performance while reducing memory usage, but also prevents nodes from storing agent-specific data. However, for cases where agents need to store and update information related to a node, Unreal Engine provides three solutions:

Instancing Nodes


■ bCreateNodeInstance variable, when set to true, will grant each agent using the Behavior Tree a unique instance of the node, at the cost of some performance and memory usage. Classes like UBTTask_BlueprintBase, UBTTask_PlayAnimation, and UBTTask_RunBehaviorDynamic, use this feature.

Storing on the blackboard

■ A common solution is to **store variables** on the **Blackboard**. To do this, expose the name of the variable from your node, then fetch and store the **Blackboard Key** using that name during the node's initialization.

o Storing on the Behavior Tree node

- You can create a **custom struct** or **class** to store variables inside the node's memory
- Many virtual functions in UBTNode take a uint8* parameter
- Override version of GetInstanceMemorySize.
- However, this memory is not part of the UObject ecosystem



```
struct FBTMoveToTaskMemory
{
    /** Move request ID */
    FAIRequestID MoveRequestID;

FDelegateHandle BBObserverDelegateHandle;
    FVector PreviousGoalLocation;

TWeakObjectPtr<UAITask_MoveTo> Task;

uint8 bWaitingForPath : 1;
    uint8 bObserverCanFinishTask : 1;
};
```


Behavior Trees - Nodes

- Behavior Tree Nodes (base class UBTNode) perform the main work of Behavior Trees, including tasks, logic flow control, and data updates.
- The node that serves as the starting point for a Behavior Tree is a **Root node**. This is a unique node within the tree, and it has a **few special rules**.
 - It can have only one connection, and it does not support attaching Decorator Nodes or Service Nodes.
 - Although the Root node has **no properties** of its own, selecting it will show the **properties** of the **Behavior Tree** in the Details panel, where you can set the Behavior Tree's **Blackboard Asset**.
- Il existe 4 types de nodes
 - Composite nodes: These are the nodes that define the root of a branch and the base rules for how that branch is executed.
 - Task nodes: These are the leaves of the Behavior Tree, these nodes are the actionable things to do and don't have an output connection.
 - Decorator nodes: Also known as conditionals. These attach to another node and make decisions on whether or not a branch in the tree, or even a single node, can be executed.
 - Service nodes: These attach to Composite nodes and will execute at their defined frequency as long as their branch is being executed. These are often used to make checks and to update the Blackboard. These take the place of traditional Parallel nodes in other Behavior Tree systems.



Behavior Trees -Composites

- Composite nodes define the root of a branch and the base rules for how that branch is executed. They can have Decorators applied to them to modify entry into their branch, or even cancel out mid-execution. Also, they can have Services attached to them that will only be active if the children of the Composite are being executed.
- Only Composite nodes can be attached to the Root node of a Behavior Tree.
- By default, there is 3 type of composite available
 - Selector
 - Selector nodes execute their children from left to right. They stop executing when one of their children succeeds. If a Selector's child succeeds, the Selector succeeds. If all the Selector's children fail, the Selector fails.
 - Sequence
 - Sequence nodes execute their children from left to right. They stop executing when one of their children fails. If a child fails, then the Sequence fails. If all the Sequence's children succeed, then the Sequence succeeds.
 - o Simple Parallel
 - The Simple Parallel node allows a **single main Task** node to be **executed alongside** of a **full tree**. When the main Task finishes, the setting in Finish Mode dictates if the node should finish immediately, aborting the secondary tree, or if it should delay for the secondary tree to finish.



Behavior Trees -Task

- Tasks are nodes that "do" things, like move an AI, or adjust Blackboard values.
 They can have Decorators or Services attached to them
- There is a **lot of task** by **default** in the engine, and the most works will comes from **you** but let's try to **highlight** some important one
 - o Finish With Result
 - The Finish With Result Task node can be used to instantly finish with a given result. This node can be used to force a branch to exit or continue based on the defined result.
 - o RunBehavior
 - The Run Behavior Task enables you to run another Behavior Tree by pushing sub-trees onto the execution stack. One limitation to consider however is that the subtree asset cannot be changed during runtime. This limitation is caused by support for the subtree's Root-level Decorators, which are injected into the Parent tree. Also, the structure of the running tree cannot be modified at runtime.
 - o Wait
 - The Wait Task can be used in the Behavior Tree to cause the tree to wait on this node until the specified Wait Time is complete.
- You can create new Tasks with your custom Blueprint logic and (or) parameters by clicking the New Task button.
- For a complete reference of existing task, check <u>Unreal Documentation</u>








Behavior Trees -Decorator


- Decorator, also known as conditionals in other Behavior Tree systems, are attached to either a Composite or a Task node and define whether or not a branch in the tree, or even a single node, can be executed.
- Again, there is a **lot of decorator** offers by **default** by the Engine, you can check the Unreal Documentation
- Let's highlight some important one
 - O Blackboard: The Blackboard node will check to see if a value is set on the given Blackboard Kev.
 - Composite: The Composite Decorator node enables you to set up more advanced logic than the built-in nodes but not as complex as a full Blueprint. Once you have added a Composite Decorator to a node, double-click the Composite Decorator to bring up the Composite's Graph. By right-clicking in the graph area you can add Decorator nodes as standalone nodes, then wire them together through AND nodes, OR nodes, and NOT nodes, to create more advanced logic
 - Conditional Loop: As long as the Key Query condition is met, this Decorator will have the node it's attached to the loop.
 - Custom Decorators: You can create new Decorators with your own custom Blueprint logic and (or) parameters by clicking the New Decorator button.





Behavior Trees -Services

- Services are special nodes associated with any Composite node (Selector, Sequence, or Simple Parallel) or Tasks, which can register for callbacks every specified amount of seconds and perform updates of various sorts that need to occur periodically.
- For example, a service can be used to determine which enemy is the best choice for the AI Pawn to pursue while the Pawn continues to act normally in its Behavior Tree toward its current enemy.
- Services are active as long as execution remains in the sub-tree of the Composite node where the service has been added
- These are often used to make **checks** and to **update** the **Blackboard**. These take the place of **traditional Parallel nodes** in other Behavior Tree systems
- Just like other nodes, you can create **Services** by clicking the **New Service button** from the **toolbar**.




Behavior Trees -Observer Aborts

- One common usage case for standard parallel nodes is to constantly check conditions so that a task can abort if the conditions it requires becomes false.
- For example, if you have a cat that performs a **sequence**, such as "**Hiss**" and "**Pounce**", you may want to **give up immediately** if the mouse **escapes** into its mouse hole.
 - With **parallel nodes**, you would have a **child** that checks if the **mouse** can be **pounced on**, and then **another child** that the sequence would **perform**.
 - Since Unreal Engine Behavior Trees are event-driven, we instead handle this by having our conditional Decorators observe their values and abort when necessary. In this example, you would have a "Mouse Can Be Pounced On?" Decorator on the Sequence, with "Observer Aborts" set to "Self".




Behavior Trees - Blackboard

- It is important to understand that a **BT** and more generally speaking **nodes** are using a **CDO** mode, which mean that you cannot save per-instance variable in them. There is some exception to handle that case we seen in the previous slide
- Blackboard is instanciated per-character which mean that it acts as a container for the variable that can be needed in the BT
- Only few types are handled, but for UObject, you can specify the base class of it
- There is an easy access from decorator to the BB values




Environment Query System (EQS)

- The Environment Query System (EQS) is a feature within the Artificial Intelligence system in Unreal Engine 5 (Unreal Engine) that is used to collect data from the environment. Within EQS, you can ask questions about the data collected through a variety of different Tests which produces an Item that best fits the type of question asked.
- An EQS Query can be called from a Behavior Tree and used to make decisions on how to proceed based on the results of your Tests. EQS Queries are primarily made up of
 - Generators, which are used to produce the locations or Actors that will be tested and weighted
 - Contexts, which are used as a frame of reference for any Tests or Generators.
- EQS Queries can be used to instruct AI characters to find the best possible location that will provide a line of sight to a player to attack, the nearest health or ammo pickup, or where the closest cover point (among other possibilities).
- Once you have a general understanding of how **Behavior Trees** work in Unreal Engine and want to have your **AI query the environment.**
- It is still an experimental implementation and therefore, EQS should not be used for production




AI Perception

- In addition to Behavior Trees which can be used to make decisions on which logic to execute, and the Environmental Query System (EQS) used to retrieve information about the environment; another tool you can use within the AI framework which provides sensory data for an AI is the AI Perception System. This provides a way for Pawns to receive data from the environment, such as where noises are coming from, if the AI was damaged by something, or if the AI sees something. This is accomplished with the AI Perception Component which acts as a stimuli listener and gathers registered Stimuli Sources.
- When a stimuli source is registered, the event On Perception Updated (or On Target Perception Updated for target selection) is called which you can use to fire off a new Blueprint Script and (or) update variables that are used to validate branches in a Behavior Tree.




AI Perception Component

- The AI Perception Component is a type of Component that can be added to a Pawn's AIController Blueprint from the Components window and is used to define what senses to listen for, the parameters for those senses, and how to respond when a sense has been detected. You can also use several different functions to get information about what was sensed, what Actors were sensed, or even disable or enable a particular type of sense.
- In addition to the common properties available in the Details panel for the AI Perception Component, you can add the type of Senses to perceive under the AI Perception and Senses Config section. Depending on the type of Sense, different properties are available to adjust how the Sense is perceived.



AI Perception Component - AI Damage Sense Config

- If you want your AI to react to damage events such as Event Any Damage, Event Point Damage, or Event Radial Damage, you can use the AI Damage Sense Config. The Implementation property (which defaults to the engine class AISense_Damage) can be used to determine how damage events are handled, however, you can create your damage classes through C++ code.
- Implementation
 - The AI Sense Class to use for these entry (defaults to AISense_Damage).
- Debug Color:
 - When using the **AI Debugging tools**, what color to draw the debug lines.
- Max Age :
 - Determines the duration in which the stimuli generated by this sense becomes forgotten (0 means never forgotten).
- Starts Enabled:
 - Determines whether the given sense starts in an enabled state or must be manually enabled/disabled.



AI Perception Component - AI Hearing

• The AI Hearing sense can be used to detect sounds generated by a Report Noise Event, for example, a projectile hits something and generates a sound that can be registered with the AI Hearing sense.

• Implementation

The AI Sense Class to use for this entry (defaults to AISense_Hearing).

Hearing range

• The **distance** in which this sense can be **perceived** by the AI Perception system.

• Lo SHearing Range

• This is used to display a different radius in the debugger for Hearing Range.

• Detection By Affiliation

Determines if Enemies, Neutrals, or Friendlies can trigger this sense.

• Debug Color


• When using the **AI Debugging tools**, what color to draw the debug lines.

• Max Age

 Determines the duration in which the stimuli generated by this sense becomes forgotten (0 means never forgotten).


Starts Enabled


 Determines whether the given sense starts in an enabled state or must be manually enabled/disabled.



AI Perception Component - AI Prediction

- This asks the Perception System to supply the Requestor with Predicted Actor's predicted location in PredictionTime seconds.
- Debug Color
 - When using the **AI Debugging tools**, what color to draw the debug lines.
- Max Age
 - Determines the **duration** in which the **stimuli** generated by this sense becomes **forgotten** (**0** means **never** forgotten).
- Starts Enabled
 - Obetermines whether the given sense starts in an enabled state or must be manually enabled/disabled.
- A common use case for **AI Prediction** is when you want your AI to be **firing** by **predicting** how **far** your player will go if he **continue** to go into the same direction
 - From that point, you'll specify who is the **requestor**, who is the **predictor actor**, and from the **prediction time** you gave, it will feed accordingly the stimuli





AI Perception Component - AI Sight

The AI Sight config enables you to define parameters that allow an AI character to
"see" things in your Level. When an Actor enters the Sight Radius, the AI
Perception System signals an update and passes through the Actor that was seen

Implementation

The AI Sense Class to use for this entry (defaults to AISense_Sight).

• Sight Radius

• The max distance over which this sense can start perceiving.

• Lose Sight Radius

• The max distance in which a seen target is no longer perceived by the sight sense.

Peripheral Vision Half Angle Degrees

How far to the **side** the AI can see in **degrees**. The value represents the **angle** measured in **relation** to the **forward vector**, not the whole range.

• Detection by Affiliation


Determines if Enemies, Neutrals, or Friendlies can trigger this sense.

Auto Success Range from Last Seen Location

• When greater than zero, the AI will always be able to see the a target that has already been seen as long as they are within the range specified here.


Debug Color / Max Age / Starts Enabled

Same as before



AI Perception Component - AI Team

- This notifies the **Perception component** owner that **someone** on the **same team** is **close** by (radius is sent by the gameplay code which sends the event).
- Debug Color / Max Age / Starts Enabled
 - Same as before




AI Perception Component - AI Touch


- The AI Touch config setting gives you the ability to detect when the AI bumps into something or something bumps into it. For example, in a stealth based game, you may want a Player to sneak by an enemy AI without touching them. Using this Sense you can determine when the Player touches the AI and can respond with different logic.
- Debug Color / Max Age / Starts Enabled
 - o Same as before



AI Perception Component - Events

- When it comes to responds to perception update, you have 5 events
- OnPerceptionUpdated
 - This Event will fire when the **Perception System** receives an **update** and will return an **array of Actors** that signaled the update.
- OnTargetPerceptionUpdated
 - Notifies all bound objects that perception info has been updated for a given target. The notification is broadcasted for any received stimulus or on change of state according to the stimulus configuration.
- OnTargetPerceptionInfoUpdated
 - This Event will fire when the Perception System receives an update and will return the Actor that signaled the update. It also returns an AI Stimulus struct that can be broken down to retrieve additional information.
- OnComponentActivated
 - An Event that is fired when the AI Perception Component is activated.
- OnComponentDeactivated
 - An Event that is fired when the AI Perception Component is deactivated.





AI Debugging

- Once you've created an AI entity you can diagnose problems or simply view what an AI is doing at any given moment using the AI Debugging Tools. Once enabled, you can cycle between viewing Behavior Trees, the Environment Query System (EQS), and the AI Perception systems all within the same centralized location.
- To enable AI Debugging, while your game is running, press the '(apostrophe) key.
- When AI Debugging panel is visible, you can access various informations from within the text and using some shortcuts
 - Numpad 0: Toggles the display of the currently available Nav Mesh data.
 - Numpad 1 : Toggles the display of the general AI debug information.
 - Numpad 2: Toggles the display of the Behavior Tree debug information.
 - Numpad 3: Toggles the display of the EQS debug information.
 - Numpad 4: Toggles the display of the AI Perception debug information.



Time to.... highlight a concept

Your turn!

Practice

• General

- We'll only be practicing in general in order to get our hand in AI programming
- Create a setup with navigation working with AI agent
 - Create different areas and place them into the work to affect the NavMesh you generated
 - Ensure to play with the values in order to understand how it makes the AI avoid some areas
 - Try to use different situation like forcing the AI to go into an area that it don't want
- Create a Behavior Tree with everything related to it in order to make a patrolling behavior
 - Idle
 - Alert
 - Track
 - Attack