Linux 系统下创建 PV 实验信息

一【实验目标】

● 学习并掌握 Linux 系统下创建 PV

二【实验环境】

- 实验机环境: Centos 6.6
- 目标机环境: Centos 6.6
- 实验拓扑:如图1所示。



图 1 实验拓扑

三【实验原理】

在 Linux 系统下,我们往往会遇到扩充磁盘的情况。普通情况下需要新加一块盘,重分区、格式化、数据复制、卸载就分区、挂载新分区等繁琐的步骤。其实,我们可以在安装系统时使用 LVM 来管理我们的文件系统,这样就可以弹性调整文件系统的容量。

四【实验步骤】

1、新加磁盘启动系统后,查看现有磁盘使用情况

(1)命令: df -h

```
[uroqt@localhost ~]$ df
File∯ystem
                       Size
                             Used Avail Use% Mounted on
/dev/mapper/VolGroup-lv root
                        50G
                                           7% /
                             3.3G
                                    44G
                                           1% /dev/shm
tmpfs
                       497M
                                   497M
                                   424M
                              29M
                                           7% /boot
/dev/sda1
                       477M
/dev/mapper/VolGroup-lv home
                        12G
                                    11G
                                          1% /home
                              30M
```

图 2

(2)命令: fdisk -l

我们发现系统已经有一个1T的磁盘sdb,这个磁盘共有1305个柱面,每个柱面大小是121597,但是还没对其分区。

Disk /dev/sdb: 1000.2 GB, 1000170586112 bytes
255 heads, 63 sectors/track, 121597 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk identifier: 0x21874022

图 3

2、对磁盘 sdb 进行分区

(1) 如果不知道 fdisk 里面的具体操作,可输入 m 进行帮助。最常用的是 n (新建) d (删除) p (打印) q (退出) t (修改系统标识符) w (写入并退出)。

命令: fdisk /dev/sdb

```
root@localhost uroot]# fdisk /dev/sdb
WARNING: DOS-compatible mode is deprecated. It's strongly recommended to 
switch off the mode (command 'c') and change display units to
          sectors (command 'u').
Command (m for help): m
Command action
      toggle a bootable flag
      edit bsd disklabel
      toggle the dos compatibility flag
       delete a partition
       list known partition types
       print this menu
      add a new partition
       create a new empty DOS partition table
      print the partition table
      quit without saving changes
       create a new empty Sun disklabel
       change a partition's system id 
change display/entry units
       verify the partition table
       write table to disk and exit
       extra functionality (experts only)
```

图 4

(2) 建立新的分区

输入 p 打印现有分区情况(还没有分区)

输入n新建分区

输入 p 为建立主分区(此时的 p 是在 n 后的,不是打印)

输入1为建立第一个主分区

分区起始位置可以直接回车,默认是1

分区最后位置为 **650** (因为每个柱面约 8M, 650 柱面约是 5G, 本实验只 5G, 剩余的做增加 LV 实验用)

输入p打印分区情况,发现已建立一个分区/dev/sdb1,但是 此分区为 Linux 格式

```
Command (m for help): p
Disk /dev/sdb: 1000.2 GB, 1000170586112 bytes
255 heads, 63 sectors/track, 121597 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk identifier: 0x00000000
   Device Boot
                       Start
                                        End
                                                   Blocks
                                                             Id System
Command (m for help): n
Command action
       extended
   e
        primary partition (1-4)
Partition number (1-4): 1
First cylinder (1-121597, default 1):
Using default value 1
Last cylinder, +cylinders or +size{K,M,G} (1-121597, default 121597): 650
Command (m for help): p
Disk /dev/sdb: 1000.2 GB, 1000170586112 bytes
255 heads, 63 sectors/track, 121597 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk identifier: 0x00000000
   Device Boot
                       Start
                                        End
                                                   Blocks
                                                             Id System
/dev/sdb1
                                        650
                                                  5221093+ 83 Linux
```

```
Command (m for help): t
Selected partition 1
Hex code (type L to list codes): L
                                          81 Minix / old Lin bf
    Empty
                    24 NEC DOS
                                                                   Solaris
                    39 Plan 9
    FAT12
                                          82
                                             Linux swap / So cl
                                                                   DRDOS/sec (FAT-
                        PartitionMagic 83
                                                                   DRDOS/sec (FAT-
 2
    XENIX root
                     3c
                                              Linux
                                                              c4
    XENIX usr
                     40
                         Venix 80286
                                          84
                                              OS/2 hidden C:
                                                              с6
                                                                   DRDOS/sec (FAT-
    FAT16 <32M
                    41
                         PPC PReP Boot
                                          85
                                              Linux extended
                                                              c7
                                                                   Syrinx
                                             NTFS volume set da
                     42
                         SFS
                                          86
                                                                   Non-FS data
    Extended
    FAT16
                     4d
                        QNX4.x
                                          87
                                              NTFS volume set db
                                                                   CP/M / CTOS /
    HPFS/NTFS
                    4e
                         QNX4.x 2nd part 88
                                             Linux plaintext de
                                                                   Dell Utility
                                                                   BootIt
 8
    AIX
                     4f
                         QNX4.x 3rd part 8e
                                             Linux LVM
                                                              df
    AIX bootable
                    50
                         OnTrack DM
                                          93
                                              Amoeba
                                                               e1
                                                                   DOS access
    OS/2 Boot Manag 51
                         OnTrack DM6 Aux 94
                                              Amoeba BBT
                                                                   DOS R/0
                                                              е3
    W95 FAT32
                     52
                                          9f
                                              BSD/0S
                         CP/M
                                                               e4
                                                                   SpeedStor
    W95 FAT32 (LBA) 53
                         OnTrack DM6 Aux a0 IBM Thinkpad hi eb
                                                                   BeOS fs
    W95 FAT16 (LBA) 54
                         OnTrackDM6
                                         a5
                                             FreeBSD
                                                                   GPT
                                                              ee
    W95 Ext'd (LBA) 55
                         EZ-Drive
                                          a6
                                              OpenBSD
                                                            ∏ ef
                                                                   EFI (FAT-12/16/
    OPUS
                         Golden Bow
                                                                  Linux/PA-RISC b
                                          a7
                                              NeXTSTEP
10
                     56
                                                               fø
    Hidden FAT12
                     5c
                         Priam Edisk
                                             Darwin UFS
                                                                  SpeedStor
ш
                                          a8
                                                               f1
    Compaq diagnost 61
                         SpeedStor
                                          a9
                                             NetBSD
                                                               f4 SpeedStor
    Hidden FAT16 <3 63
                         GNU HURD or Sys ab
                                             Darwin boot
                                                               f2 DOS secondary
                         Novell Netware af
Novell Netware b7
                                             HFS / HFS+
BSDI fs
                                                                  VMware VMFS
VMware VMKCORE
16
    Hidden FAT16
                   64
                                                               fb
    Hidden HPFS/NTF 65
17
   AST SmartSleep 70
                         DiskSecure Mult b8
                                              BSDI swap
                                                               fd
                                                                  Linux raid auto
   Hidden W95 FAT3 75
                                             Boot Wizard hid fe
                         PC/IX
                                         bb
                                                                   LANstep
1c Hidden W95 FAT3 80
                                                               ff
                         Old Minix
                                         be
                                             Solaris boot
                                                                   ввт
le Hidden W95 FAT1
Hex code (type L to list codes): 8e
Changed system type of partition 1 to 8e (Linux LVM)
Command (m for help): p
Disk /dev/sdb: 1000.2 GB, 1000170586112 bytes
255 heads, 63 sectors/track, 121597 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk identifier: 0x00000000
   Device Boot
                     Start
                                   End
                                             Blocks
                                                      Id System
/dev/sdb1
                                   650
                                            5221093+
                                                          Linux LVM
                                                      8e
                         1
Command (m for help): w
The partition table has been altered!
Calling ioctl() to re-read partition table.
```

图 6

改变系统标识符:

输入t改变分区1的属性

输入L查看有个属性对应的命令

输入 8e 改变分区 1 为 Linux LVM 格式

输入p打印分区情况,发现建立的分区/dev/sdb1 为 Linux LVM 格式

tip:再次使用 **fdisk -l** 查看系统内磁盘情况发现 /dev/sdb 上已有一个 Linux LVM 格式的 /**dev/sdb1** 分区

```
Disk /dev/sdb: 1000.2 GB, 1000170586112 bytes
255 heads, 63 sectors/track, 121597 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk identifier: 0x00000000
   Device Boot
                    Start
                                  End
                                            Blocks
                                                     Id
                                                         System
                                  650
/dev/sdb1
                                           5221093+
                                                         Linux LVM
                        1
                                                     8e
```

图 7

使 kernel 重新读取分区表

命令: partprobe

对于 /dev/sda 的警告不予理会

```
[root@centos6 ~]# partprobe
Warning: WARNING: the kernel failed to re-read the partition table on /dev/sda (
Device or resource busy). As a result, it may not reflect all of your changes u
ntil after reboot. SEAGLE
```

图 8

3、创建 PV:

扫面系统 PV: pvscan

创建 PV: pvcreate /dev/sdb1

查看 PV: pvdisplay

这样我们就创建了一个 4.98G 的 PV, 注意 Allocatable 为 NO

```
[root@localhost Desktop]# pvscan
PV /dev/sda2 VG VolGroup lvm2 [63.51 GiB / 0 free]
Total: 1 [63.51 GiB] / in use: 1 [63.51 GiB] / in no VG: 0 [0 [root@localhost Desktop]# pvcreate
Please enter a physical volume path
  Run `pvcreate --help' for more information.
[root@localhost Desktop]# pvcreate /dev/sdb1
Physical volume "/dev/sdb1" successfully created
[root@localhost Desktop]# pvscan
                     VG VolGroup
                                        lvm2 [63.51 GiB / 0
  PV /dev/sda2
                                                                       free]
  PV /dev/sdb1
                                         lvm2 [4.98 GiB]
Total: 2 [68.49 GiB] / in use: 1 [63.51 GiB] / in no VG: 1 [4.98 GiB] [root@localhost Desktop]# pvdisplay
   --- Physical volume --
  PV Name
                               /dev/sda2
  VG Name
                               VolGroup
  PV Size
                               63.51 GiB / not usable 3.00 MiB
                               yes (but full)
  Allocatable
  PE Size
                                4.00 MiB
  Total PE
                               16258
  Free PE
  Allocated PE
                               16258
  PV UUID
                               4bR5c3-h4YE-cPlI-Djep-zJnQ-86SD-zRADRy
   "/dev/sdb1" is a new physical volume of "4.98 GiB"
   --- NEW Physical volume ---
  PV Name
                                /dev/sdb1
  VG Name
  PV Size
                               4.98 GiB
  Allocatable
                               NO
  PE Size
                               Θ
  Total PE
                                Θ
                               Θ
  Free PE
  Allocated PE
   PV UUID
                                6UaEvL-8CTs-JFRB-9Rix-EGiH-77mq-dLKZA0
```

五【实验思考】

- 使用 fdisk 命令进行分区。
- partprobe, kernel 重新读取分区表。