







# **GALAHAD**

DQP

USER DOCUMENTATION

GALAHAD Optimization Library version 4.0

## 1 SUMMARY

This package uses a dual gradient-projection method to solve the strictly-convex quadratic-programming problem

minimize 
$$q(\mathbf{x}) \stackrel{\text{def}}{=} \frac{1}{2} \mathbf{x}^T \mathbf{H} \mathbf{x} + \mathbf{g}^T \mathbf{x} + f$$
 (1.1)

or the shifted least-distance problem

minimize 
$$s(\mathbf{x}) \stackrel{\text{def}}{=} \frac{1}{2} \sum_{j=1}^{n} w_j^2 (x_j - x_j^0)^2 + \mathbf{g}^T \mathbf{x} + f$$
 (1.2)

subject to the general linear constraints

$$c_i^l \leq \mathbf{a}_i^T \mathbf{x} \leq c_i^u, \quad i = 1, \dots, m,$$

and the simple bound constraints

$$x_{j}^{l} \le x_{j} \le x_{j}^{u}, \quad j = 1, \dots, n,$$
 (1.3)

where the *n* by *n* symmetric, positive-definite matrix **H**, the vectors **g**, **w**,  $\mathbf{x}^0$ ,  $\mathbf{a}_i$ ,  $\mathbf{c}^l$ ,  $\mathbf{c}^u$ ,  $\mathbf{x}^l$ ,  $\mathbf{x}^u$  and the scalar *f* are given. Any of the constraint bounds  $c_i^l$ ,  $c_i^u$ ,  $x_j^l$  and  $x_j^u$  may be infinite. Full advantage is taken of any zero coefficients in the matrix **H** or the matrix **A** of vectors  $\mathbf{a}_i$ .

The package may also be used to minimize the penalty functions

$$q(\mathbf{x}) + \rho \sum_{i=1}^{m} \max \left( c_i^l - \mathbf{a}_i^T \mathbf{x}, \mathbf{a}_i^T \mathbf{x} - c_i^u, 0 \right) \text{ or } s(\mathbf{x}) + \rho \sum_{i=1}^{m} \max \left( c_i^l - \mathbf{a}_i^T \mathbf{x}, \mathbf{a}_i^T \mathbf{x} - c_i^u, 0 \right)$$

subject to the simple bound constraints (1.3).

ATTRIBUTES — Versions: GALAHAD\_DQP\_single, GALAHAD\_DQP\_double. Uses: GALAHAD\_CLOCK, GALAHAD\_SYMBOLS, GALAHAD\_STRING, GALAHAD\_SPACE, GALAHAD\_SPECFILE, GALAHAD\_SMT, GALAHAD\_QPT, GALAHAD\_QPP, GALAHAD\_QPP, GALAHAD\_SPDD, GALAHAD\_SDRT, GALAHAD\_SDRT, GALAHAD\_SDRT, GALAHAD\_NORMS. Date: August 2012. Origin: N. I. M. Gould, Rutherford Appleton Laboratory. Language: Fortran 95 + TR 15581 or Fortran 2003. Parallelism: Some options may use OpenMP and its runtime library.

## 2 HOW TO USE THE PACKAGE

Access to the package requires a USE statement such as

Single precision version

USE GALAHAD\_DQP\_single

Double precision version

USE GALAHAD\_DQP\_double

If it is required to use both modules at the same time, the derived types SMT\_type, QPT\_problem\_type, NLPT\_userdata\_type, DQP\_time\_type, DQP\_control\_type, DQP\_inform\_type and DQP\_data\_type (Section 2.4) and the subroutines DQP\_initialize, DQP\_solve, DQP\_terminate, (Section 2.5) and DQP\_read\_specfile (Section 2.7) must be renamed on one of the USE statements.

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

DQP GALAHAD ■

#### 2.1 Matrix storage formats

Both the Hessian matrix **H** and the constraint Jacobian **A**, the matrix whose rows are the vectors  $\mathbf{a}_i^T$ ,  $i = 1, \dots, m$ , may be stored in a variety of input formats.

#### 2.1.1 Dense storage format

The matrix **A** is stored as a compact dense matrix by rows, that is, the values of the entries of each row in turn are stored in order within an appropriate real one-dimensional array. Component n\*(i-1)+j of the storage array A%val will hold the value  $a_{ij}$  for  $i=1,\ldots,m,\ j=1,\ldots,n$ . Since **H** is symmetric, only the lower triangular part (that is the part  $h_{ij}$  for  $1 \le j \le i \le n$ ) need be held. In this case the lower triangle will be stored by rows, that is component i\*(i-1)/2+j of the storage array H%val will hold the value  $h_{ij}$  (and, by symmetry,  $h_{ji}$ ) for  $1 \le j \le i \le n$ .

#### 2.1.2 Sparse co-ordinate storage format

Only the nonzero entries of the matrices are stored. For the l-th entry of  $\mathbf{A}$ , its row index i, column index j and value  $a_{ij}$  are stored in the l-th components of the integer arrays A%row, A%col and real array A%val, respectively. The order is unimportant, but the total number of entries A%ne is also required. The same scheme is applicable to  $\mathbf{H}$  (thus requiring integer arrays H%row, H%col, a real array H%val and an integer value H%ne), except that only the entries in the lower triangle need be stored.

#### 2.1.3 Sparse row-wise storage format

Again only the nonzero entries are stored, but this time they are ordered so that those in row i appear directly before those in row i+1. For the i-th row of  $\mathbf{A}$ , the i-th component of a integer array  $\mathbb{A}$ -ptr holds the position of the first entry in this row, while  $\mathbb{A}$ -ptr (m+1) holds the total number of entries plus one. The column indices j and values  $a_{ij}$  of the entries in the i-th row are stored in components  $l = \mathbb{A}$ -ptr  $(i), \ldots, \mathbb{A}$ -ptr (i+1)-1 of the integer array  $\mathbb{A}$ -col, and real array  $\mathbb{A}$ -val, respectively. The same scheme is applicable to  $\mathbf{H}$  (thus requiring integer arrays  $\mathbb{H}$ -ptr,  $\mathbb{H}$ -col, and a real array  $\mathbb{A}$ -val), except that only the entries in the lower triangle need be stored.

For sparse matrices, this scheme almost always requires less storage than its predecessor.

# 2.1.4 Diagonal storage format

If **H** is diagonal (i.e.,  $h_{ij} = 0$  for all  $1 \le i \ne j \le n$ ) only the diagonals entries  $h_{ii}$ ,  $1 \le i \le n$ , need be stored, and the first n components of the array H%val may be used for the purpose. There is no sensible equivalent for the non-square **A**.

#### 2.1.5 Scaled-identity-matrix storage format

If **H** is a scalar multiple of the identity matrix (i.e.,  $h_{ii} = h_{11}$  and  $h_{ij} = 0$  for all  $1 \le i \ne j \le n$ ) only the first diagonal entry  $h_{11}$  needs be stored, and the first component of the array H%val may be used for the purpose. Again, there is no sensible equivalent for the non-square **A**.

## 2.1.6 Identity-matrix storage format

If **H** is the identity matrix (i.e.,  $h_{ii} = 1$  and  $h_{ij} = 0$  for all  $1 \le i \ne j \le n$ ), no explicit entries needs be stored.

# 2.1.7 Zero-matrix storage format

If  $\mathbf{0} = 0$  (i.e.,  $h_{ij} = 0$  for all  $1 \le i, j \le n$ ), no explicit entries needs be stored.

#### 2.2 Integer kinds

We use the term long INTEGER to denote INTEGER (kind=long), where long = selected\_int\_kind(18)).

## 2.3 OpenMP

OpenMP may be used by the GALAHAD\_DQP package to provide parallelism for some solver options in shared memory environments. See the documentation for the GALAHAD package SLS for more details. To run in parallel, OpenMP must be enabled at compilation time by using the correct compiler flag (usually some variant of -openmp). The number of threads may be controlled at runtime by setting the environment variable OMP\_NUM\_THREADS.

The code may be compiled and run in serial mode.

## 2.4 The derived data types

Ten derived data types are accessible from the package.

## 2.4.1 The derived data type for holding matrices

The derived data type SMT\_TYPE is used to hold the matrices A and H. The components of SMT\_TYPE used here are:

- m is a scalar component of type default INTEGER, that holds the number of rows in the matrix.
- n is a scalar component of type default INTEGER, that holds the number of columns in the matrix.
- ne is a scalar variable of type default INTEGER, that holds the number of matrix entries.
- type is a rank-one allocatable array of type default CHARACTER, that is used to indicate the matrix storage scheme used. Its precise length and content depends on the type of matrix to be stored (see §2.4.2).
- is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_DQP\_double) and dimension at least ne, that holds the values of the entries. Each pair of off-diagonal entries  $h_{ij} = h_{ji}$  of a *symmetric* matrix **H** is represented as a single entry (see §2.1.1–2.1.3). Any duplicated entries that appear in the sparse co-ordinate or row-wise schemes will be summed.
- row is a rank-one allocatable array of type default INTEGER, and dimension at least ne, that may hold the row indices of the entries. (see §2.1.2).
- is a rank-one allocatable array of type default INTEGER, and dimension at least ne, that may the column indices of the entries (see §2.1.2–2.1.3).
- ptr is a rank-one allocatable array of type default INTEGER, and dimension at least m + 1, that may hold the pointers to the first entry in each row (see §2.1.3).

# 2.4.2 The derived data type for holding the problem

The derived data type QPT\_problem\_type is used to hold the problem. The components of QPT\_problem\_type are:

- n is a scalar variable of type default INTEGER, that holds the number of optimization variables, n.
- m is a scalar variable of type default INTEGER, that holds the number of general linear constraints, m.

Hessian\_kind is a scalar variable of type default INTEGER, that is used to indicate what type of Hessian the problem involves. Possible values for Hessian\_kind are:

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

<0 In this case, a general quadratic program of the form (1.1) is given. The Hessian matrix **H** will be provided in the component H (see below).

- 0 In this case, a linear program, that is a problem of the form (1.2) with weights  $\mathbf{w} = 0$ , is given.
- 1 In this case, a least-distance problem of the form (1.2) with weights  $w_i = 1$  for j = 1, ..., n is given.
- >1 In this case, a weighted least-distance problem of the form (1.2) with general weights **w** is given. The weights will be provided in the component WEIGHT (see below).
- is scalar variable of type SMT\_TYPE that holds the Hessian matrix  ${\bf H}$  whenever Hessian\_kind < 0. The following components are used:
  - H%type is an allocatable array of rank one and type default CHARACTER, that is used to indicate the storage scheme used. If the dense storage scheme (see Section 2.1.1) is used, the first five components of H%type must contain the string DENSE. For the sparse co-ordinate scheme (see Section 2.1.2), the first ten components of H%type must contain the string COORDINATE, for the sparse row-wise storage scheme (see Section 2.1.3), the first fourteen components of H%type must contain the string SPARSE\_BY\_ROWS, and for the diagonal storage scheme (see Section 2.1.4), the first eight components of H%type must contain the string DIAGONAL, for the scaled-identity matrix storage scheme (see Section 2.1.5), the first fifteen components of H%type must contain the string SCALED\_IDENTITY, for the identity matrix storage scheme (see Section 2.1.6), the first eight components of H%type must contain the string IDENTITY, and for the zero matrix storage scheme (see Section 2.1.7), the first four components of H%type must contain the string ZERO.

For convenience, the procedure SMT\_put may be used to allocate sufficient space and insert the required keyword into H%type. For example, if prob is of derived type DQP\_problem\_type and involves a Hessian we wish to store using the co-ordinate scheme, we may simply

```
CALL SMT_put( prob%H%type, 'COORDINATE', istat )
```

See the documentation for the GALAHAD package SMT for further details on the use of SMT\_put.

- Hane is a scalar variable of type default INTEGER, that holds the number of entries in the **lower triangular** part of **H** in the sparse co-ordinate storage scheme (see Section 2.1.2). It need not be set for any of the other schemes.
- H%val is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_DQP\_double), that holds the values of the entries of the **lower triangular** part of the Hessian matrix **H** in any of non-trivial storage schemes mentioned in Sections 2.1.2–2.1.4. For the scaled-identity scheme (see Section 2.1.5), the first component, H%val(1), holds the scale factor  $h_{11}$ . It need not be allocated for any of the remaining schemes.
- H%row is a rank-one allocatable array of type default INTEGER, that holds the row indices of the **lower triangular** part of **H** in the sparse co-ordinate storage scheme (see Section 2.1.2). It need not be allocated for any of the other schemes.
- H%col is a rank-one allocatable array variable of type default INTEGER, that holds the column indices of the **lower triangular** part of **H** in either the sparse co-ordinate (see Section 2.1.2), or the sparse row-wise (see Section 2.1.3) storage scheme. It need not be allocated when any of the other storage schemes are used.
- H%ptr is a rank-one allocatable array of dimension n+1 and type default INTEGER, that holds the starting position of each row of the **lower triangular** part of **H**, as well as the total number of entries plus one, in the sparse row-wise storage scheme (see Section 2.1.3). It need not be allocated when the other schemes are used.

If  $Hessian\_kind \ge 0$ , the components of H need not be set.

- WEIGHT is a rank-one allocatable array type default REAL (double precision in GALAHAD\_DQP\_double), that should be allocated to have length n, and its j-th component filled with the value  $w_j$  for  $j=1,\ldots,n$ , whenever Hessian\_kind > 1. If Hessian\_kind  $\le 1$ , WEIGHT need not be allocated.
- target\_kind is a scalar variable of type default INTEGER, that is used to indicate whether the components of the targets  $\mathbf{x}^0$  (if they are used) have special or general values. Possible values for target\_kind are:
  - 0 In this case,  $\mathbf{x}^0 = 0$ .
  - 1 In this case,  $x_i^0 = 1$  for j = 1, ..., n.
  - $\neq$  0,1 In this case, general values of  $\mathbf{x}^0$  will be used, and will be provided in the component X0 (see below).
- is a rank-one allocatable array type default REAL (double precision in GALAHAD\_DQP\_double), that should be allocated to have length n, and its j-th component filled with the value  $x_j^0$  for  $j=1,\ldots,n$ , whenever Hessian\_kind >0 and target\_kind  $\neq 0,1$ . If Hessian\_kind  $\leq 0$  or target\_kind =0,1, X0 need not be allocated.
- gradient\_kind is a scalar variable of type default INTEGER, that is used to indicate whether the components of the gradient g have special or general values. Possible values for gradient\_kind are:
  - 0 In this case,  $\mathbf{g} = 0$ .
  - 1 In this case,  $g_j = 1$  for j = 1, ..., n.
  - $\neq$  0,1 In this case, general values of **g** will be used, and will be provided in the component G (see below).
- is a rank-one allocatable array type default REAL (double precision in GALAHAD\_DQP\_double), that should be allocated to have length n, and its j-th component filled with the value  $g_j$  for  $j = 1, \ldots, n$ , whenever gradient\_kind  $\neq 0,1$ . If gradient\_kind = 0, 1, G need not be allocated.
- is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that holds the constant term, f, in the objective function.
- is scalar variable of type SMT\_TYPE that holds the Jacobian matrix **A** when it is available explicitly. The following components are used:
  - A%type is an allocatable array of rank one and type default CHARACTER, that is used to indicate the storage scheme used. If the dense storage scheme (see Section 2.1.1) is used, the first five components of A%type must contain the string DENSE. For the sparse co-ordinate scheme (see Section 2.1.2), the first ten components of A%type must contain the string COORDINATE, while for the sparse row-wise storage scheme (see Section 2.1.3), the first fourteen components of A%type must contain the string SPARSE\_BY\_ROWS.

Just as for H%type above, the procedure SMT\_put may be used to allocate sufficient space and insert the required keyword into A%type. Once again, if prob is of derived type DQP\_problem\_type and involves a Jacobian we wish to store using the sparse row-wise storage scheme, we may simply

```
CALL SMT_put( prob%A%type, 'SPARSE_BY_ROWS', istat )
```

- A%ne is a scalar variable of type default INTEGER, that holds the number of entries in **A** in the sparse co-ordinate storage scheme (see Section 2.1.2). It need not be set for either of the other two appropriate schemes.
- A%val is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_DQP\_double), that holds the values of the entries of the Jacobian matrix **A** in any of the appropriate storage schemes discussed in Section 2.1.
- A%row is a rank-one allocatable array of type default INTEGER, that holds the row indices of **A** in the sparse coordinate storage scheme (see Section 2.1.2). It need not be allocated for either of the other two appropriate schemes.

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

DQP GALAHAD ■

A%col is a rank-one allocatable array variable of type default INTEGER, that holds the column indices of **A** in either the sparse co-ordinate (see Section 2.1.2), or the sparse row-wise (see Section 2.1.3) storage scheme. It need not be allocated when the dense storage scheme is used.

- A%ptr is a rank-one allocatable array of dimension m+1 and type default INTEGER, that holds the starting position of each row of **A**, as well as the total number of entries plus one, in the sparse row-wise storage scheme (see Section 2.1.3). It need not be allocated when the other appropriate schemes are used.
- c\_l is a rank-one allocatable array of dimension m and type default REAL (double precision in GALAHAD\_DQP\_double), that holds the vector of lower bounds  $\mathbf{c}^l$  on the general constraints. The *i*-th component of C\_l, i = 1, ..., m, contains  $\mathbf{c}^l_i$ . Infinite bounds are allowed by setting the corresponding components of C\_l to any value smaller than -infinity, where infinity is a component of the control array control (see Section 2.4.3).
- is a rank-one allocatable array of dimension m and type default REAL (double precision in GALAHAD\_DQP\_double), that holds the vector of upper bounds  $\mathbf{c}^u$  on the general constraints. The *i*-th component of C\_u, i = 1, ..., m, contains  $\mathbf{c}^u_i$ . Infinite bounds are allowed by setting the corresponding components of C\_u to any value larger than infinity, where infinity is a component of the control array control (see Section 2.4.3).
- is a rank-one allocatable array of dimension n and type default REAL (double precision in GALAHAD\_DQP\_double), that holds the vector of lower bounds  $\mathbf{x}^l$  on the the variables. The j-th component of X\_1,  $j = 1, \ldots, n$ , contains  $\mathbf{x}^l_j$ . Infinite bounds are allowed by setting the corresponding components of X\_1 to any value smaller than -infinity, where infinity is a component of the control array control (see Section 2.4.3).
- X\_u is a rank-one allocatable array of dimension n and type default REAL (double precision in GALAHAD\_DQP\_double), that holds the vector of upper bounds  $\mathbf{x}^u$  on the variables. The *j*-th component of X\_u,  $j = 1, \ldots, n$ , contains  $\mathbf{x}^u_j$ . Infinite bounds are allowed by setting the corresponding components of X\_u to any value larger than that infinity, where infinity is a component of the control array control (see Section 2.4.3).
- is a rank-one allocatable array of dimension n and type default REAL (double precision in GALAHAD\_DQP\_double), that holds the values **x** of the optimization variables. The *j*-th component of X, j = 1, ..., n, contains  $x_i$ .
- is a rank-one allocatable array of dimension m and type default REAL (double precision in GALAHAD\_DQP\_double), that holds the values  $\mathbf{A}\mathbf{x}$  of the constraints. The *i*-th component of  $\mathbb{C}$ , i = 1, ..., m, contains  $\mathbf{a}_i^T \mathbf{x} \equiv (\mathbf{A}\mathbf{x})_i$ .
- is a rank-one allocatable array of dimension m and type default REAL (double precision in GALAHAD\_DQP\_double), that holds the values  $\mathbf{y}$  of estimates of the Lagrange multipliers corresponding to the general linear constraints (see § 4). The i-th component of  $\mathbf{y}$ ,  $i = 1, \dots, m$ , contains  $y_i$ .
- is a rank-one allocatable array of dimension n and type default REAL (double precision in GALAHAD\_DQP\_double), that holds the values **z** of estimates of the dual variables corresponding to the simple bound constraints (see § 4). The *j*-th component of  $\mathbb{Z}$ ,  $j = 1, \ldots, n$ , contains  $z_j$ .

## 2.4.3 The derived data type for holding control parameters

The derived data type DQP\_control\_type is used to hold controlling data. Default values may be obtained by calling DQP\_initialize (see Section 2.5.1), while components may also be changed by calling DQP\_read\_specfile (see Section 2.7.1). The components of DQP\_control\_type are:

- error is a scalar variable of type default INTEGER, that holds the stream number for error messages. Printing of error messages in DQP\_solve and DQP\_terminate is suppressed if error  $\leq 0$ . The default is error = 6.
- out is a scalar variable of type default INTEGER, that holds the stream number for informational messages. Printing of informational messages in DQP\_solve is suppressed if out < 0. The default is out = 6.

- print\_level is a scalar variable of type default INTEGER, that is used to control the amount of informational output which is required. No informational output will occur if print\_level  $\leq 0$ . If print\_level = 1, a single line of output will be produced for each iteration of the process. If print\_level  $\geq 2$ , this output will be increased to provide significant detail of each iteration. The default is print\_level = 0.
- start\_print is a scalar variable of type default INTEGER, that specifies the first iteration for which printing will occur in DQP\_solve. If start\_print is negative, printing will occur from the outset. The default is start\_print = -1.
- stop\_print is a scalar variable of type default INTEGER, that specifies the last iteration for which printing will occur in DQP\_solve. If stop\_print is negative, printing will occur once it has been started by start\_print. The default is stop\_print = -1.
- print\_gap is a scalar variable of type default INTEGER. Once printing has been started, output will occur once every print\_gap iterations. If print\_gap is no larger than 1, printing will be permitted on every iteration. The default is print\_gap = 1.
- maxit is a scalar variable of type default INTEGER, that holds the maximum number of iterations which will be allowed in DQP\_solve. The default is maxit = 1000.
- max\_sc is a scalar variable of type default INTEGER, that specifies the maximum number of columns permitted in the Schur complement of the reference matrix (see Section 4) before a refactorization is triggered when there is no Fredholm Alternative. The default is max\_sc = 100.
- cauchy\_only is a scalar variable of type default INTEGER, that specifies the maximum number of changes in the active set that may occur in the first-phase projected-dual-gradient arc search during an iteration before attempting a second phase unconstrained minimization in the space of free dual variables § 4). If cauchy\_only is negative, the second phase will always be tried. The default is cauchy\_only = -1.
- arc\_search\_maxit is a scalar variable of type default INTEGER, that holds the maximum number of steps that may be performed by the arc-search every iteration. If arc\_search\_maxit is set to a negative number, as many steps as are necessary will be performed. The default is arc\_search\_maxit = -1.
- cg\_maxit is a scalar variable of type default INTEGER, that holds the maximum number of conjugate-gradient inner iterations that may be performed during the computation of each search direction in DQP\_solve. If cg\_maxit is set to a negative number, it will be reset by DQP\_solve to the dimension of the relevant linear system +1. The default is cg\_maxit = 1000.
- dual\_starting\_point is a scalar variable of type default INTEGER, that specifies how the algorithm computes its staring point. Possible values are:
  - 0 the values y and z provided by the user in components Y and Z of the derived data type QPT\_problem\_type will be used.
  - 1 values obtained by minimizing a linearized version of the dual will be used.
  - 2 values obtained by minimizing a simplified quadratic version of the dual will be used.
  - 3 values will be chosen so that all dual variables lie away from their bounds if possible. This corresponds to trying to start from a point in which all primal constraints are active.
  - 4 values will be chosen so that all dual variables lie on their bounds if possible. This corresponds to trying to start from a point in which all primal constraints are inactive.

Any other value will be interpreted as dual\_starting\_point = 0, and this is the default.

restore\_problem is a scalar variable of type default INTEGER, that specifies how much of the input problem is to be restored on output. Possible values are:

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

- 0 nothing is restored.
- 1 the vector data  $\mathbf{w}$ ,  $\mathbf{g}$ ,  $\mathbf{c}^l$ ,  $\mathbf{c}^u$ ,  $\mathbf{x}^l$ , and  $\mathbf{x}^u$  will be restored to their input values.
- 2 the entire problem, that is the above vector data along with the Jacobian matrix A, will be restored.

The default is restore\_problem = 2.

- rho is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that holds the penalty weight,  $\rho$ . If rho > 0, the general linear constraints are not enforced explicitly, but instead included in the objective as a penalty term weighted by  $\rho$ . If rho  $\leq$  0, the general linear constraints are explicit (that is, there is no penalty term in the objective function) The default is rho = 0.0.
- infinity is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that is used to specify which constraint bounds are infinite. Any bound larger than infinity in modulus will be regarded as infinite. The default is infinity =  $10^{19}$ .
- stop\_abs\_p and stop\_rel\_p are scalar variables of type default REAL (double precision in GALAHAD\_DQP\_double), that hold the required absolute and relative accuracy for the primal infeasibility (see Section 4). The absolute value of each component of the primal infeasibility on exit is required to be smaller than the larger of stop\_abs\_p and stop\_rel\_p times a "typical value" for this component. The defaults are stop\_abs\_p = stop\_rel\_p =  $u^{1/3}$ , where u is EPSILON(1.0) (EPSILON(1.0D0) in GALAHAD\_DQP\_double).
- stop\_abs\_d and stop\_rel\_d are scalar variables of type default REAL (double precision in GALAHAD\_DQP\_double), that hold the required absolute and relative accuracy for the dual infeasibility (see Section 4). The absolute value of each component of the dual infeasibility on exit is required to be smaller than the larger of stop\_abs\_p and stop\_rel\_p times a "typical value" for this component. The defaults are stop\_abs\_d = stop\_rel\_d =  $u^{1/3}$ , where u is EPSILON(1.0) (EPSILON(1.0D0) in GALAHAD\_DQP\_double).
- stop\_abs\_c and stop\_rel\_c are scalar variables of type default REAL (double precision in GALAHAD\_DQP\_double), that hold the required absolute and relative accuracy for the violation of complementary slackness (see Section 4). The absolute value of each component of the complementary slackness on exit is required to be smaller than the larger of stop\_abs\_p and stop\_rel\_p times a "typical value" for this component. The defaults are stop\_abs\_c = stop\_rel\_c =  $u^{1/3}$ , where u is EPSILON(1.0) (EPSILON(1.0D0) in GALAHAD\_DQP\_double).
- stop\_cg\_relative and stop\_cg\_absolute are scalar variables of type default REAL (double precision in GALAH-AD\_DQP\_double), that hold the relative and absolute convergence tolerances for the conjugate-gradient iteration that occurs in the face of currently-active constraints that may be used to construct the search direction. \_stop\_cg\_relative = 0.01 and stop\_cg\_absolute =  $\sqrt{u}$ , where u is EPSILON(1.0) (EPSILON(1.0D0) in GALAHAD\_DQP\_double).
- cg\_zero\_curvature is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double) that specifies the threshold below which any curvature encountered by the conjugate-gradient iteration is regarded as zero. The default is cq\_zero\_curvature = 10u, where u is EPSILON(1.0) (EPSILON(1.0D0) in GALAHAD\_DQP\_double).
- identical\_bounds\_tol is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double). Each pair of variable bounds  $(x_j^l, x_j^u)$  that is closer than identical\_bounds\_tol will be reset to the average of their values,  $\frac{1}{2}(x_j^l + x_j^u)$ . The default is identical\_bounds\_tol = u, where u is EPSILON(1.0) (EPSILON(1.0D0) in GALAHAD\_DQP\_double).
- cpu\_time\_limit is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that is used to specify the maximum permitted CPU time. Any negative value indicates no limit will be imposed. The default is cpu\_time\_limit = 1.0.
- clock\_time\_limit is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that is used to specify the maximum permitted elapsed system clock time. Any negative value indicates no limit will be imposed. The default is clock\_time\_limit = 1.0.

- remove\_dependencies is a scalar variable of type default LOGICAL, that must be set .TRUE. if the algorithm is to attempt to remove any linearly dependent constraints before solving the problem, and .FALSE. otherwise. We recommend removing linearly dependencies. The default is remove\_dependencies = .TRUE..
- treat\_zero\_bounds\_as\_general is a scalar variable of type default LOGICAL. If it is set to .FALSE., variables which are only bounded on one side, and whose bound is zero, will be recognised as non-negativities/non-positivities rather than simply as lower- or upper-bounded variables. If it is set to .TRUE., any variable bound  $x_j^l$  or  $x_j^u$  which has the value 0.0 will be treated as if it had a general value. Setting treat\_zero\_bounds\_as\_general to .TRUE. has the advantage that if a sequence of problems are reordered, then bounds which are "accidentally" zero will be considered to have the same structure as those which are nonzero. However, GALAHAD\_DQP is able to take special advantage of non-negativities/non-positivities, so if a single problem, or if a sequence of problems whose bound structure is known not to change, is/are to be solved, it will pay to set the variable to .FALSE.. The default is treat\_zero\_bounds\_as\_general = .FALSE..
- exact\_arc\_search is a scalar variable of type default LOGICAL, that must be set .TRUE. if the user wishes to perform an exact arc search and .FALSE. if an inexact search suffices. Usually the exact search is beneficial, but occasionally it may be more expensive. The default is exact\_arc\_search = .TRUE..
- subspace\_direct is a scalar variable of type default LOGICAL, that must be set .TRUE. if the user wishes to compute subspace steps using matrix factorization, and .FALSE. if conjugate-gradient steps are preferred. Factorization often produces a better step, but sometimes the conjugate-gradient method may be less expensive and less demanding on storage. The default is subspace\_direct = .FALSE., but if more advanced symmetric linear solvers such as MA57 or MA97 available, we recommend setting subspace\_direct = .TRUE. and changing symmetric\_linear\_solver (see below) appropriately.
- subspace\_arc\_search is a scalar variable of type default LOGICAL, that must be set .TRUE. if the user wishes to perform an arc search following the subspace step and .FALSE. if a step to the nearest inactive bound suffices.

  As before, the exact search is usually beneficial, but it is more expensive. The default is subspace\_arc\_search = .TRUE..
- space\_critical is a scalar variable of type default LOGICAL, that must be set .TRUE. if space is critical when allocating arrays and .FALSE. otherwise. The package may run faster if space\_critical is .FALSE. but at the possible expense of a larger storage requirement. The default is space\_critical = .FALSE..
- deallocate\_error\_fatal is a scalar variable of type default LOGICAL, that must be set .TRUE. if the user wishes to terminate execution if a deallocation fails, and .FALSE. if an attempt to continue will be made. The default is deallocate\_error\_fatal = .FALSE..
- symmetric\_linear\_solver is a scalar variable of type default CHARACTER and length 30, that specifies the external package to be used to solve any symmetric linear system that might arise. Current possible choices are 'sils', 'ma27', 'ma57', 'ma77', 'ma86', 'ma97', ssids, 'pardiso' and 'wsmp'. See the documentation for the GALAHAD package SLS for further details. Since 'sils' does not currently provide the required Fredholm Alternative option, the default is symmetric\_linear\_solver = 'ma57', but we recommend 'ma97' if it is available.
- definite\_linear\_solver is a scalar variable of type default CHARACTER and length 30, that specifies the external package to be used to solve any symmetric positive-definite linear system that might arise. Current possible choices are 'sils', 'ma27', 'ma57', 'ma77', 'ma86', 'ma87', 'ma97', ssids, 'pardiso' and 'wsmp'. See the documentation for the GALAHAD package SLS for further details. The default is definite\_linear\_solver = 'sils', but we recommend 'ma87' if it available.
- unsymmetric\_linear\_solver is a scalar variable of type default CHARACTER and length 30, that specifies the external package to be used to solve any unsymmetric linear systems that might arise. Possible choices are 'gls', 'ma28' and 'ma48', although only 'gls' is installed by default. See the documentation for the GALAHAD

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

- package ULS for further details. The default is unsymmetric\_linear\_solver = 'gls', but we recommend 'ma48' if it available.
- prefix is a scalar variable of type default CHARACTER and length 30, that may be used to provide a user-selected character string to preface every line of printed output. Specifically, each line of output will be prefaced by the string prefix (2:LEN(TRIM(prefix))-1), thus ignoring the first and last non-null components of the supplied string. If the user does not want to preface lines by such a string, they may use the default prefix = "".
- FDC\_control is a scalar variable of type FDC\_control\_type whose components are used to control any detection of linear dependencies performed by the package GALAHAD\_FDC. See the specification sheet for the package GALAHAD\_FDC for details, and appropriate default values.
- SLS\_control is a scalar variable of type SLS\_control\_type whose components are used to control factorizations performed by the package GALAHAD\_SLS. See the specification sheet for the package GALAHAD\_SLS for details, and appropriate default values.
- SBLS\_control is a scalar variable of type SBLS\_control\_type whose components are used to control factorizations performed by the package GALAHAD\_SBLS. See the specification sheet for the package GALAHAD\_SBLS for details, and appropriate default values.
- GLTR\_control is a scalar variable of type GLTR\_control\_type whose components are used to control conjugate-gradient solves performed by the package GALAHAD\_GLTR. See the specification sheet for the package GALAH-AD\_GLTR for details, and appropriate default values.

## 2.4.4 The derived data type for holding timing information

The derived data type DQP\_time\_type is used to hold elapsed CPU and system clock times for the various parts of the calculation. The components of DQP\_time\_type are:

- total is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the total CPU time spent in the package.
- preprocess is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the CPU time spent preprocess the problem prior to solution.
- find\_dependent is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the CPU time spent detecting and removing dependent constraints prior to solution.
- analyse is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the CPU time spent analysing the required matrices prior to factorization.
- factorize is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the CPU time spent factorizing the required matrices.
- solve is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the CPU time spent computing the search direction.
- search is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the CPU time spent in the arc search.
- clock\_total is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the total elapsed system clock time spent in the package.
- clock\_preprocess is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the elapsed system clock time spent preprocess the problem prior to solution.

- clock\_find\_dependent is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the elapsed system clock time spent detecting and removing dependent constraints prior to solution.
- clock\_analyse is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the elapsed system clock time spent analysing the required matrices prior to factorization.
- clock\_factorize is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the elapsed system clock time spent factorizing the required matrices.
- clock\_solve is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the elapsed system clock time spent computing the search direction.
- clock\_search is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that gives the elapsed system clock time spent in the arc search.

## 2.4.5 The derived data type for holding informational parameters

The derived data type DQP\_inform\_type is used to hold parameters that give information about the progress and needs of the algorithm. The components of DQP\_inform\_type are:

- status is a scalar variable of type default INTEGER, that gives the exit status of the algorithm. See Section 2.6 for details.
- alloc\_status is a scalar variable of type default INTEGER, that gives the status of the last attempted array allocation or deallocation. This will be 0 if status = 0.
- bad\_alloc is a scalar variable of type default CHARACTER and length 80, that gives the name of the last internal array for which there were allocation or deallocation errors. This will be the null string if status = 0.
- iter is a scalar variable of type default INTEGER, that gives the number of iterations performed.
- factorization\_status is a scalar variable of type default INTEGER, that gives the return status from the matrix factorization.
- factorization\_integer is a scalar variable of type long INTEGER, that gives the amount of integer storage used for the matrix factorization.
- factorization\_real is a scalar variable of type long INTEGER, that gives the amount of real storage used for the matrix factorization.
- nfacts is a scalar variable of type default INTEGER, that gives the total number of factorizations performed.
- threads is a scalar variable of type default INTEGER, that gives the total number of threads used for parallel execution.
- obj is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that holds the value of the objective function at the best estimate of the solution found.
- primal\_infeasibility is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that holds the  $\ell_{\infty}$ -norm of the violation of primal optimality (see Section 2.4.4) at the best estimate of the solution found.
- dual\_infeasibility is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that holds the  $\ell_{\infty}$ -norm of the violation of dual optimality (see Section 2.4.4) at the best estimate of the solution found.
- complementary\_slackness is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that holds the absolute value of the violation of complementary slackness (see Section 2.4.4) at the best estimate of the solution found.

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

non\_negligible\_pivot is a scalar variable of type default REAL (double precision in GALAHAD\_DQP\_double), that holds the value of the smallest pivot that was not judged to be zero when searching for dependent linear constraints.

- feasible is a scalar variable of type default LOGICAL, that has the value .TRUE. if the output value of  $\boldsymbol{x}$  satisfies the constraints, and the value .FALSE. otherwise.
- time is a scalar variable of type DQP\_time\_type whose components are used to hold elapsed CPU and system clock times for the various parts of the calculation (see Section 2.4.4).
- FDC\_inform is a scalar variable of type FDC\_inform\_type whose components are used to provide information about any detection of linear dependencies performed by the package GALAHAD\_FDC. See the specification sheet for the package GALAHAD\_FDC for details.
- SLS\_inform is a scalar variable of type SLS\_inform\_type whose components are used to provide information about factorizations performed by the package GALAHAD\_SLS. See the specification sheet for the package GALAHAD\_SLS for details.
- SBLS\_inform is a scalar variable of type SBLS\_inform\_type whose components are used to provide information about factorizations performed by the package GALAHAD\_SBLS. See the specification sheet for the package GALAHAD\_SBLS for details.
- GLTR\_inform is a scalar variable of type GLTR\_info\_type whose components are used to provide information about the step calculation performed by the package GALAHAD\_GLTR. See the specification sheet for the package GALAHAD\_GLTR for details.

# 2.4.6 The derived data type for holding problem data

The derived data type DQP\_data\_type is used to hold all the data for a particular problem, or sequences of problems with the same structure, between calls of DQP procedures. This data should be preserved, untouched, from the initial call to DQP\_initialize to the final call to DQP\_terminate.

## 2.5 Argument lists and calling sequences

There are three procedures for user calls (see Section 2.7 for further features):

- 1. The subroutine DQP\_initialize is used to set default values, and initialize private data, before solving one or more problems with the same sparsity and bound structure.
- 2. The subroutine DQP\_solve is called to solve the problem.
- 3. The subroutine DQP\_terminate is provided to allow the user to automatically deallocate array components of the private data, allocated by DQP\_solve, at the end of the solution process.

We use square brackets [ ] to indicate OPTIONAL arguments.

#### 2.5.1 The initialization subroutine

Default values are provided as follows:

```
CALL DQP_initialize( data, control, inform )
```

data is a scalar INTENT (INOUT) argument of type DQP\_data\_type (see Section 2.4.6). It is used to hold data about the problem being solved.

- control is a scalar INTENT (OUT) argument of type DQP\_control\_type (see Section 2.4.3). On exit, control contains default values for the components as described in Section 2.4.3. These values should only be changed after calling DQP\_initialize.
- inform is a scalar INTENT (OUT) argument of type DQP\_inform\_type (see Section 2.4.5). A successful call to DQP\_initialize is indicated when the component status has the value 0. For other return values of status, see Section 2.6.

# 2.5.2 The quadratic programming subroutine

The quadratic programming solution algorithm is called as follows:

```
CALL DQP_solve( prob, data, control, inform[, C_stat, X_stat])
```

prob is a scalar INTENT (INOUT) argument of type QPT\_problem\_type (see Section 2.4.2). It is used to hold data about the problem being solved. The user must allocate all the array components, and set values for all components except prob%C.

The components prob%X , prob%Y and prob%Z must be set to initial estimates of the primal variables,  $\mathbf{x}$ , Lagrange multipliers,  $\mathbf{y}$ , for the general constraints and dual variables for the bound constraints,  $\mathbf{z}$ , respectively. Inappropriate initial values will be altered, so the user should not be overly concerned if suitable values are not apparent, and may be content with merely setting prob%X=0.0, prob%Y=0.0 and prob%Z=0.0.

On exit, the components prob%X, prob%C, prob%Y, and prob%Z will contain the best estimates of the primal variables  $\mathbf{x}$ , the linear constraints  $A\mathbf{x}$ , Lagrange multipliers,  $\mathbf{y}$ , for the general constraints and dual variables for the bound constraints  $\mathbf{z}$ , respectively. **Restrictions:** prob%n > 0, prob%m  $\geq$  0, prob%A\_type  $\in$  {'DENSE', 'COORDINATE', 'SPARSE\_BY\_ROWS'}, and (if  $\mathbf{H}$  is provided) prob%H%ne  $\geq$  -2. prob%H\_type  $\in$  {'DENSE', 'COORDINATE', 'SPARSE\_BY\_ROWS', 'DIAGONAL'}.

- data is a scalar INTENT (INOUT) argument of type DQP\_data\_type (see Section 2.4.6). It is used to hold data about the problem being solved. It must not have been altered by the user since the last call to DQP\_initialize.
- control is a scalar INTENT(IN) argument of type DQP\_control\_type (see Section 2.4.3). Default values may be assigned by calling DQP\_initialize prior to the first call to DQP\_solve.
- inform is a scalar INTENT (INOUT) argument of type DQP\_inform\_type (see Section 2.4.5). A successful call to DQP\_solve is indicated when the component status has the value 0. For other return values of status, see Section 2.6.
- C\_stat is an OPTIONAL rank-one INTENT(OUT) array argument of dimension p%m and type default INTEGER, that indicates which of the general linear constraints are in the optimal active set. Possible values for C\_stat(i),  $i=1,\ldots,p$ %m, and their meanings are
  - <0 the *i*-th general constraint is in the active set, on its lower bound,
  - >0 the *i*-th general constraint is in the active set, on its upper bound, and
  - 0 the *i*-th general constraint is not in the active set.
- X\_stat is an OPTIONAL rank-one INTENT(OUT) array argument of dimension p%n and type default INTEGER, that indicates which of the simple bound constraints are in the current active set. Possible values for X\_stat(j),  $j=1,\ldots,p$ %n, and their meanings are
  - <0 the *j*-th simple bound constraint is in the active set, on its lower bound,
  - >0 the j-th simple bound constraint is in the active set, on its upper bound, and
  - 0 the *j*-th simple bound constraint is not in the active set.

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

DQP GALAHAD

#### 2.5.3 The termination subroutine

All previously allocated arrays are deallocated as follows:

```
CALL DQP_terminate( data, control, inform )
```

data is a scalar INTENT (INOUT) argument of type DQP\_data\_type exactly as for DQP\_solve, which must not have been altered by the user since the last call to DQP\_initialize. On exit, array components will have been deallocated.

control is a scalar INTENT(IN) argument of type DQP\_control\_type exactly as for DQP\_solve.

inform is a scalar INTENT (OUT) argument of type DQP\_inform\_type exactly as for DQP\_solve. Only the component status will be set on exit, and a successful call to DQP\_terminate is indicated when this component status has the value 0. For other return values of status, see Section 2.6.

## 2.6 Warning and error messages

A negative value of inform%status on exit from DQP\_solve or DQP\_terminate indicates that an error has occurred. No further calls should be made until the error has been corrected. Possible values are:

- -1. An allocation error occurred. A message indicating the offending array is written on unit control%error, and the returned allocation status and a string containing the name of the offending array are held in inform%alloc\_status and inform%bad\_alloc respectively.
- -2. A deallocation error occurred. A message indicating the offending array is written on unit control%error and the returned allocation status and a string containing the name of the offending array are held in inform%alloc\_status and inform%bad\_alloc respectively.
- -3. One of the restrictions prob%n > 0, prob%m ≥ 0 the requirement that prob%A\_type contain its relevant string 'DENSE', 'COORDINATE' or 'SPARSE\_BY\_ROWS', or the requirement that prob%H\_type contain its relevant string 'DENSE', 'COORDINATE', 'SPARSE\_BY\_ROWS' or 'DIAGONAL' when **H** is available, has been violated.
- -4. The bound constraints are inconsistent.
- -5. The constraints appear to have no feasible point.
- -9. The analysis phase of the factorization failed; the return status from the factorization package is given in the component inform%factor\_status.
- -10. The factorization failed; the return status from the factorization package is given in the component inform%factor\_status.
- -16. The problem is so ill-conditioned that further progress is impossible.
- -17. The step is too small to make further impact.
- -18. Too many iterations have been performed. This may happen if control%maxit is too small, but may also be symptomatic of a badly scaled problem.
- -19. The elapsed CPU or system clock time limit has been reached. This may happen if either control%cpu\_time\_limit or control%clock\_time\_limit is too small, but may also be symptomatic of a badly scaled problem.
- -20. The matrix **H** does not appear to be positive definite.
- -23. An entry from the strict upper triangle of **H** has been specified.

#### 2.7 Further features

In this section, we describe an alternative means of setting control parameters, that is components of the variable control of type DQP\_control\_type (see Section 2.4.3), by reading an appropriate data specification file using the subroutine DQP\_read\_specifile. This facility is useful as it allows a user to change DQP control parameters without editing and recompiling programs that call DQP.

A specification file, or specifie, is a data file containing a number of "specification commands". Each command occurs on a separate line, and comprises a "keyword", which is a string (in a close-to-natural language) used to identify a control parameter, and an (optional) "value", which defines the value to be assigned to the given control parameter. All keywords and values are case insensitive, keywords may be preceded by one or more blanks but values must not contain blanks, and each value must be separated from its keyword by at least one blank. Values must not contain more than 30 characters, and each line of the specifie is limited to 80 characters, including the blanks separating keyword and value.

The portion of the specification file used by DQP\_read\_specfile must start with a "BEGIN DQP" command and end with an "END" command. The syntax of the specifie is thus defined as follows:

where keyword and value are two strings separated by (at least) one blank. The "BEGIN DQP" and "END" delimiter command lines may contain additional (trailing) strings so long as such strings are separated by one or more blanks, so that lines such as

```
BEGIN DQP SPECIFICATION

and

END DQP SPECIFICATION
```

are acceptable. Furthermore, between the "BEGIN DQP" and "END" delimiters, specification commands may occur in any order. Blank lines and lines whose first non-blank character is ! or \* are ignored. The content of a line after a ! or \* character is also ignored (as is the ! or \* character itself). This provides an easy manner to "comment out" some specification commands, or to comment specific values of certain control parameters.

The value of a control parameters may be of three different types, namely integer, logical or real. Integer and real values may be expressed in any relevant Fortran integer and floating-point formats (respectively). Permitted values for logical parameters are "ON", "TRUE", ".TRUE.", "T", "YES", "Y", or "OFF", "NO", "N", "FALSE", ".FALSE." and "F". Empty values are also allowed for logical control parameters, and are interpreted as "TRUE".

The specification file must be open for input when DQP\_read\_specfile is called, and the associated device number passed to the routine in device (see below). Note that the corresponding file is REWINDed, which makes it possible to combine the specifications for more than one program/routine. For the same reason, the file is not closed by DQP\_read\_specfile.

# 2.7.1 To read control parameters from a specification file

Control parameters may be read from a file as follows:

```
CALL DQP_read_specfile( control, device )
```

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

DQP GALAHAD

control is a scalar INTENT (INOUT) argument of type DQP\_control\_type (see Section 2.4.3). Default values should have already been set, perhaps by calling DQP\_initialize. On exit, individual components of control may have been changed according to the commands found in the specifile. Specifile commands and the component (see Section 2.4.3) of control that each affects are given in Table 2.1.

command	component of control	value type
error-printout-device	%error	integer
printout-device	%out	integer
print-level	%print_level	integer
start-print	%start_print	integer
stop-print	%stop_print	integer
iterations-between-printing	%print_gap	integer
maximum-number-of-iterations	%maxit	integer
maximum-dimension-of-schur-complement	%max_schur_complement	integer
cauchy-only-until-change-level	%cauchy_only	integer
maximum-number-of-steps-per-arc-search	%arc_search_maxit	integer
maximum-number-of-cg-iterations-per-iteration	%cg_maxit	integer
dual-starting-point	%dual_starting_point	integer
restore-problem-on-output	%restore_problem	integer
penalty-weight	%rho	real
infinity-value	%infinity	real
identical-bounds-tolerance	%identical_bounds_tol	real
absolute-primal-accuracy	%stop_abs_p	real
relative-primal-accuracy	%stop_rel_p	real
absolute-dual-accuracy	%stop_abs_d	real
relative-dual-accuracy	%stop_rel_d	real
absolute-complementary-slackness-accuracy	%stop_abs_c	real
relative-complementary-slackness-accuracy	%stop_rel_c	real
cg-relative-accuracy-required	%stop_cg_relative	real
cg-absolute-accuracy-required	%stop_cg_absolute	real
zero-curvature-threshold	%cg_zero_curvature	real
identical-bounds-tolerance	%identical_bounds_tol	real
maximum-cpu-time-limit	%cpu_time_limit	real
maximum-clock-time-limit	%clock_time_limit	real
remove-linear-dependencies	%remove_dependencies	logical
treat-zero-bounds-as-general	%treat_zero_bounds_as_general	logical
perform-exact-arc-search	%exact_arc_search	logical
direct-solution-of-subspace-problem	%subspace_direct	logical
perform-subspace-arc-search	%subspace_arc_search	logical
space-critical	%space_critical	logical
deallocate-error-fatal	%deallocate_error_fatal	logical
symmetric-linear-equation-solver	%symmetric_linear_solver	character
definite-linear-equation-solver	%definite_linear_solver	character
unsymmetric-linear-equation-solver	%unsymmetric_linear_solver	character
output-line-prefix	%prefix	character

Table 2.1: Specfile commands and associated components of control.

device is a scalar INTENT (IN) argument of type default INTEGER, that must be set to the unit number on which the specifle has been opened. If device is not open, control will not be altered and execution will continue, but

an error message will be printed on unit control%error.

#### 2.8 Information printed

If  $control print_level$  is positive, information about the progress of the algorithm will be printed on unit  $control control control print_level = 1$ , a single line of output will be produced for each iteration of the process. This will include values of the current dual objective value (this should converge to minus the optimal primal objective value), the primal infeasibility, the numbers of currently active constraints and the numbers that have changed during the iteration for both the arc search and the subspace step and the elapsed CPU time in seconds.

If control\*print\_level  $\geq 2$  this output will be increased to provide significant detail of each iteration. This extra output includes a record of where in the iteration the algorithm is, residuals of the linear systems solved, and, for larger values of control\*print\_level, values of the primal and dual variables and Lagrange multipliers.

# **3 GENERAL INFORMATION**

Use of common: None.

Workspace: Provided automatically by the module.

Other routines called directly: None.

Other modules used directly: DQP\_solve calls the GALAHAD packages GALAHAD\_CLOCK, GALAHAD\_SYMBOLS, GALAHAD\_STRING, GALAHAD\_SPACE, GALAHAD\_SPECFILE, GALAHAD\_SMT, GALAHAD\_QPT, GALAHAD\_QPP, GALAHAD\_QPD, GALAHAD\_SPECFILE, GALAHAD\_SBLS, GALAHAD\_SCU, GALAHAD\_GLRT and GALAHAD\_NORMS.

Input/output: Output is under control of the arguments control%error, control%out and control%print\_level.

Restrictions: prob%n > 0, prob%m  $\ge 0$ , prob%A\_type and prob%H\_type  $\in \{' \text{DENSE'}, ' \text{COORDINATE'}, ' \text{SPARSE_BY_ROWS'}, ' \text{DIAGONAL'} \}$ . (if **H** and **A** are explicit).

**Portability:** ISO Fortran 95 + TR 15581 or Fortran 2003. The package is thread-safe.

# 4 METHOD

The required solution  $\mathbf{x}$  necessarily satisfies the primal optimality conditions

$$\mathbf{A}\mathbf{x} = \mathbf{c} \tag{4.1}$$

and

$$\mathbf{c}^l < \mathbf{c} < \mathbf{c}^u, \ \mathbf{x}^l < \mathbf{x} < \mathbf{x}^u, \tag{4.2}$$

the dual optimality conditions

$$\mathbf{H}\mathbf{x} + \mathbf{g} = \mathbf{A}^T \mathbf{y} + \mathbf{z}$$
 (or  $\mathbf{W}^2(\mathbf{x} - \mathbf{x}^0) + \mathbf{g} = \mathbf{A}^T \mathbf{y} + \mathbf{z}$  for the least-distance type objective) (4.3)

where

$$\mathbf{y} = \mathbf{y}^{l} + \mathbf{y}^{u}, \ \mathbf{z} = \mathbf{z}^{l} + \mathbf{z}^{u}, \ \mathbf{y}^{l} > 0, \ \mathbf{y}^{u} < 0, \ \mathbf{z}^{l} > 0 \ \text{and} \ \mathbf{z}^{u} < 0,$$
 (4.4)

and the complementary slackness conditions

$$(\mathbf{A}\mathbf{x} - \mathbf{c}^l)^T \mathbf{y}^l = 0, \ (\mathbf{A}\mathbf{x} - \mathbf{c}^u)^T \mathbf{y}^u = 0, \ (\mathbf{x} - \mathbf{x}^l)^T \mathbf{z}^l = 0 \ \text{and} \ (\mathbf{x} - \mathbf{x}^u)^T \mathbf{z}^u = 0,$$
(4.5)

where the diagonal matrix  $\mathbf{W}^2$  has diagonal entries  $w_j^2$ , j = 1, ..., n, where the vectors  $\mathbf{y}$  and  $\mathbf{z}$  are known as the Lagrange multipliers for the general linear constraints, and the dual variables for the bounds, respectively, and where the vector inequalities hold component-wise.

Dual gradient-projection methods solve (1.1) by instead solving the dual quadratic program

minimize 
$$q^D(\mathbf{y}^l, \mathbf{y}^u, \mathbf{z}^l, \mathbf{z}^u) = \frac{1}{2}[(\mathbf{y}^l + \mathbf{y}^u)^T A + (\mathbf{z}^l + \mathbf{z}^u)^T) H^{-1}[A^T(\mathbf{y}^l + \mathbf{y}^u) + \mathbf{z}^l + \mathbf{z}^u] - [(\mathbf{y}^l + \mathbf{y}^u)^T A + (\mathbf{z}^l + \mathbf{z}^u)^T) H^{-1} g - (\mathbf{c}^{lT} \mathbf{y}^l + \mathbf{c}^{uT} \mathbf{y}^u + \mathbf{x}^{lT} \mathbf{z}^l + \mathbf{x}^{uT} \mathbf{z}^u)$$
 subject to  $(\mathbf{y}^l, \mathbf{z}^l) \ge 0$  and  $(\mathbf{y}^u, \mathbf{z}^u) \le 0$ , (4.6)

and then recovering the required solution from the linear system

$$\mathbf{H}\mathbf{x} = -\mathbf{g} + A^T(\mathbf{y}^l + \mathbf{y}^u) + \mathbf{z}^l + \mathbf{z}^u.$$

The dual problem (4.6) is solved by an accelerated gradient-projection method comprising of alternating phases in which (i) the current projected dual gradient is traced downhill (the 'arc search') as far as possible and (ii) the dual variables that are currently on their bounds are temporarily fixed and the unconstrained minimizer of  $q^D(\mathbf{y}^l, \mathbf{y}^u, \mathbf{z}^l, \mathbf{z}^u)$  with respect to the remaining variables is sought; the minimizer in the second phase may itself need to be projected back into the dual feasible region (either using a brute-force backtrack or a second arc search).

Both phases require the solution of sparse systems of symmetric linear equations, and these are handled by the GALAHAD matrix factorization package GALAHAD\_SBLS or the conjugate-gradient package GALAHAD\_GLTR. The systems are commonly singular, and this leads to a requirement to find the Fredholm Alternative for the given matrix and its right-hand side. In the non-singular case, there is an option to update existing factorizations using the "Schurcomplement" approach given by the package GALAHAD\_SCU.

Optionally, the problem may be pre-processed temporarily to eliminate dependent constraints using the package GALAHAD\_FDC. This may improve the performance of the subsequent iteration.

## **References:**

The basic algorithm is described in

N. I. M. Gould and D. P. Robinson, "A dual gradient-projection method for large-scale strictly-convex quadratic problems", Computational Optimization and Applications **67(1)** (2017) 1-38.

## 5 EXAMPLE OF USE

Suppose we wish to minimize  $\frac{1}{2}x_1^2 + x_2^2 + x_2x_3 + \frac{3}{2}x_3^2 + 2x_2 + 1$  subject to the general linear constraints  $1 \le 2x_1 + x_2 \le 2$  and  $x_2 + x_3 = 2$ , and simple bounds  $-1 \le x_1 \le 1$  and  $x_3 \le 2$ . Then, on writing the data for this problem as

$$\mathbf{H} = \begin{pmatrix} 1 & & \\ & 2 & 1 \\ & 1 & 3 \end{pmatrix}, \ \mathbf{g} = \begin{pmatrix} 0 \\ 2 \\ 0 \end{pmatrix}, \ \mathbf{x}^l = \begin{pmatrix} -1 \\ -\infty \\ -\infty \end{pmatrix}, \ \mathbf{x}^u = \begin{pmatrix} 1 \\ \infty \\ 2 \end{pmatrix}$$

and

$$\mathbf{A} = \begin{pmatrix} 2 & 1 \\ & 1 & 1 \end{pmatrix}, \ \mathbf{c}^l = \begin{pmatrix} 1 \\ 2 \end{pmatrix}, \ \text{and} \ \mathbf{c}^u = \begin{pmatrix} 2 \\ 2 \end{pmatrix}$$

in sparse co-ordinate format, we may use the following code:

```
! THIS VERSION: GALAHAD 2.5 - 01/08/2012 AT 08:00 GMT.

PROGRAM GALAHAD_DQP_EXAMPLE

USE GALAHAD_DQP_double ! double precision version

IMPLICIT NONE

INTEGER, PARAMETER :: wp = KIND( 1.0D+0 ) ! set precision
```

```
REAL (KIND = wp), PARAMETER :: infinity = 10.0_wp ** 20
  TYPE ( QPT_problem_type ) :: p
  TYPE ( DQP_data_type ) :: data
  TYPE ( DQP_control_type ) :: control
  TYPE ( DQP_inform_type ) :: inform
  INTEGER :: s
  INTEGER, PARAMETER :: n = 3, m = 2, h_ne = 4, a_ne = 4
  INTEGER, ALLOCATABLE, DIMENSION( : ) :: C_stat, X_stat
! start problem data
  ALLOCATE( p%G( n ), p%X_1( n ), p%X_u( n ) )
  ALLOCATE( p%C( m ), p%C_1( m ), p%C_u( m ) )
  ALLOCATE( p%X( n ), p%Y( m ), p%Z( n ))
  ALLOCATE( X_stat( n ), C_stat( m ) )
  p%new_problem_structure = .TRUE.
                                           ! new structure
  p%n = n ; p%m = m ; p%f = 1.0_wp
                                           ! dimensions & objective constant
                                           ! objective gradient
  p%G = (/ 0.0_wp, 2.0_wp, 0.0_wp /)
  p%C_1 = (/ 1.0_wp, 2.0_wp /)
                                            ! constraint lower bound
                                     ! constraint upper bound
  p\C_u = (/ 2.0_wp, 2.0_wp /)
  p%X_1 = (/ - 1.0_wp, - infinity, - infinity /) ! variable lower bound
  p%X_u = (/1.0_wp, infinity, 2.0_wp /)! variable upper bound
  p%X = 0.0_{wp}; p%Y = 0.0_{wp}; p%Z = 0.0_{wp}! start from zero
! sparse co-ordinate storage format
  CALL SMT_put(p%H%type, 'COORDINATE', s) ! Specify co-ordinate
  CALL SMT_put(p%A%type, 'COORDINATE', s) ! storage for H and A
  ALLOCATE( p%H%val( h_ne ), p%H%row( h_ne ), p%H%col( h_ne ) )
  ALLOCATE( p%A%val( a_ne ), p%A%row( a_ne ), p%A%col( a_ne ) )
  p%H%val = (/ 1.0_wp, 2.0_wp, 1.0_wp, 3.0_wp /) ! Hessian H
  p%H%row = (/ 1, 2, 3, 3 /)
                                                ! NB lower triangle
  p%H%col = (/ 1, 2, 2, 3 /) ; p%H%ne = h_ne
  p%A%val = (/ 2.0_wp, 1.0_wp, 1.0_wp, 1.0_wp /) ! Jacobian A
  p%A%row = (/ 1, 1, 2, 2 /)
  p%A%col = (/ 1, 2, 2, 3 /) ; p%A%ne = a_ne
! problem data complete
  CALL DQP_initialize( data, control, inform ) ! Initialize control parameters
  control%print_level = 1
                                             ! Set infinity
  control%infinity = infinity
  CALL DQP_solve(p, data, control, inform, C_stat, X_stat) ! Solve
  IF ( inform%status == 0 ) THEN
                                             ! Successful return
    WRITE( 6, "(' DQP: ', IO, ' iterations ', /,
                                                                              S.
        ' Optimal objective value =', ES12.4, /,
   δ
         ' Optimal solution = ', ( 5ES12.4 ) )" ) inform%iter, inform%obj, p%X
   S.
  ELSE
                                              ! Error returns
    WRITE( 6, "( ' DQP_solve exit status = ', I6 ) " ) inform%status
  CALL DQP_terminate( data, control, inform ) ! delete internal workspace
  END PROGRAM GALAHAD_DQP_EXAMPLE
```

# This produces the following output:

```
DQP: 1 iterations
Optimal objective value = 6.3462E+00
Optimal solution = 1.5385E-01 6.9231E-01 1.3077E+00
```

The same problem may be solved holding the Hessian data in a sparse row-wise storage format by replacing the relevant lines in

! sparse co-ordinate storage format

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

DQP GALAHAD

or using a dense storage format with the replacement lines

#### respectively.

If instead **H** had been the diagonal matrix

$$\mathbf{H} = \left(\begin{array}{cc} 1 & & \\ & 2 & \\ & & 3 \end{array}\right)$$

but the other data is as before, the diagonal storage scheme might be used for H, and in this case we would instead

```
CALL SMT_put( prob%H%type, 'DIAGONAL', s ) ! Specify dense storage for H ALLOCATE( p%H%val( n ) ) p%H%val = (/ 1.0_wp, 2.0_wp, 3.0_wp /) ! Hessian values
```