NetSim Multi-Parameter Sweep Program

Software Recommended:

NetSim v13.0 (32/64 bit), DOT NET CORE SDK 3.1, Python 3.7.4

Project Download Link:

https://github.com/NetSim-TETCOS/Multi-Parameter-Sweeper v13.0/archive/refs/heads/main.zip

Introduction:

When users want to *sweep* one or more parameters, they change their values between simulation runs, and compare and analyse the performance metrics from each run. NetSim multi-parameter sweeper enables users to automate the sweep process.


Consider an example, where a user wishes to create and simulate a network scenario for all possible values of one or more parameters in combination and analyse a set of performance metrics across the simulation runs. This is extremely time consuming to do manually using the NetSim GUI.

The multi-parameter sweep program enables users to automate the sweep process across multiple input parameters, simulate each run, save each result, and compare specific output metrics via a spreadsheet software like MS Excel.

The sweep program runs NetSim via its CLI interface.

File Organization

The project directory consists of several binaries which are responsible for different tasks during a multi-parameter sweep:



1. **input.xml**: This file contains the base NetSim network configuration that is to be simulated. This file is created by copy pasting the Configuration.netsim file that can be obtained by saving a network configuration in NetSim and renaming it to input.xml.

```
Edit View Project Debug XML Test Analyze Tools
                                           Extensions Window Help
                                           ▶ Attach... → 🎜 🚳 🚽
 | 🏗 - 🏊 🖺 🚜 | り - 🤉
     <?xml version="1.0" encoding="UTF-8" standalone="no"?>
   E<TETCOS_NETSIM xmlns:ns0="http://www.w3.org/2001/XMLSchema-instance" ns0:noNamespaceSchema</pre>
       <experiment_information>...</experiment_information>
11 🛓
       <GUI_INFORMATION>.../GUI_INFORMATION>
       <NETWORK_CONFIGURATION>
         <DEVICE_CONFIGURATION DEVICE_COUNT="4">
           KDEVICE DEFAULT_DEVICE_NAME="gNB" DEVICE_ID="1" DEVICE_IMAGE="gNB.png" DEVICE_NAME
           <DEVICE DEFAULT DEVICE_NAME="EPC" DEVICE_ID="2" DEVICE_IMAGE="EPC.png" DEVICE_NAME</pre>
            <DEVICE DEFAULT DEVICE NAME=</pre>
                                         "Wired Node
           <DEVICE DEFAULT DEVICE NAME:</pre>
                                         ="UE" DEVICE_ID="4"
           KLINK DEVICE COUNT="2" LINK COLOR="" LINK ID="1" LINK MODE="FULL DUPLEX" LINK NAME:
           <LINK DEVICE_COUNT=
                                                  LINK_ID="2
                                                               LINK MODE=
           <LINK DEVICE
                                                         LINK_ID=
           KAPPLICATION APPLICATION_COLOR="0x9000ffff" APPLICATION_METHOD="UNICAST" APPLICATION
        /METLIORY COMETCURATION:
```

The values of parameters which are to be varied during each simulation run needs to be specified as {0}, {1}, {2}, etc. respectively.

For Example, if the X and Y coordinates of a device is to be varied the values can be modified in the input.xml file as shown below:

```
🙀 <u>F</u>ile <u>E</u>dit <u>V</u>iew <u>P</u>roject <u>D</u>ebug <u>X</u>ML Te<u>s</u>t A<u>n</u>alyze <u>T</u>ools E<u>x</u>tensions <u>W</u>indow <u>H</u>elp Search (Ctrl+Q) 🔑
 G - 🖯 🏗 - 🚈 🖺 🛂 🦻 - 🤉
                                                          ▶ Attach... - 👼 🌀 _
                                                                                                                | Live Share
            <?xml version="1.0" encoding="UTF-8" standalone="no"?>
         □<TETCOS_NETSIM xmlns:ns0="http://www.w3.org/2001/XMLSchema-instance" ns0:noNamespaceSchema
              <EXPERIMENT_INFORMATION>...</EXPERIMENT_INFORMATION>
         GUI INFORMATION>...</GUI INFORMATION>
     18 - <NETWORK_CONFIGURATION>
                <DEVICE_CONFIGURATION DEVICE_COUNT="4">
                   cDEVICE DEFAULT_DEVICE_NAME="gNB" DEVICE_ID="1" DEVICE_IMAGE="gNB.png" DEVICE_NAME
kDEVICE DEFAULT_DEVICE_NAME="EPC" DEVICE_ID="2" DEVICE_IMAGE="EPC.png" DEVICE_NAME
                   <DEVICE DEFAULT DEVICE_NAME="Wired_Node" DEVICE_ID="3" DEVICE_IMAGE="WiredNode.
<DEVICE DEFAULT DEVICE NAME="UE" DEVICE ID="4" DEVICE_IMAGE="UserEquipment.png"</pre>
                                                                                         DEVICE IMAGE="WiredNode.png
                     <POS_3D X_OR_LON="{0}" Y_OR_LAT="{1}" Z="0">
                        <MOBILITY MODEL="NO_MOBILITY"/>
                     </POS 3D>
    172 E
                     <INTERFACE ID="1" INTERFACE_TYPE="LTE NR">
                        <LAYER TYPE="NETWORK LAYER":</pre>
                          <NETWORK PROTOCOL NAME="IPV4" SETPROPERTY="TRUE">
                             <PROTOCOL PROPERTY DEFAULT GATEWAY="11.2.1.1" IP ADDRESS="11.2.1.2" SUBNET N</pre>
                           </NETWORK PROTOCOL>
         © 0 △ 2 ← → TVDE_"DATALTME LAVED"
                                                                                                     ▶ Ln: 169 Ch: 53 SPC CRLF
```


2. **Script.txt:** This file should be updated with the parameter from the output metrics of NetSim that is to be logged at the end of each simulation run for the purpose of analysis. At the end of every simulation, NetSim generates a Metrics.xml file which contain the performance metrics written in a specific format based on which it is loaded in the results dashboard.

Each Metric is part of a results table which can be accessed using a menu in the results dashboard.


A NetSim Metrics.xml file is shown below:

```
⋉ Eile Edit <u>V</u>iew <u>P</u>roject <u>D</u>ebug XML Tegt A<u>n</u>alyze <u>T</u>ools Extensions <u>W</u>indow <u>H</u>elp
 G - O 18 - 👝 🖺 🛂 🦻 - 🤉
                                                                         ▶ Attach... - 🎜 🚳 _
                                                                                                                                                           | ← Live Share
              x input.xml*
     383 ☐ <MENU Name="Application_Metrics">
               <TABLE name="Application_Metrics">
    <TH name="Application Id" isShow="true"/>
                 <TH name="Throughput Plot" isShow="true"/>
<TH name="Application Name" isShow="true"/>
<TH name="Source Id" isShow="false"/>
                 <TH name="Packet generated" isShow="true"/>
<TH name="Packet received" isShow="true"/>
                 <TH name="Payload generated (bytes)" isShow="false"/>
                 <TH name="Payload received (bytes)" isShow="false"/</pre>
                  <TH name="Throughput (Mbps)" isShow="true"/>
                 <TH name="Delay(microsec)" isShow="true"/>
<TH name="Jitter(microsec)" isShow="true"/>
                   <TC Value="1"/>
                    <TC Value="App1 CBR"/>
                   <TC Value="3"
                   <TC Value="25000"/
                   <TC Value="17946"/>
                   <TC Value="36500000"
                   <TC Value="4192.185600"/>
<TC Value="7188.952970"/>
            No issues found
                                                                                                                                                     Ln: 458 Ch: 1 SPC LF
```

For Example, if the application throughput is to be logged for each simulation run then the scrip file can be updated as shown below:



- 3. **ConfigWriter.exe**: This executable takes one or more command line arguments as input and generated Configuration.netsim file by replacing the arguments in place of the variable parameters specified in the input.xml file.
- If there are two variable parameters specified in the input.xml file ({0} and {1}) then two arguments need to be passed while calling ConfigWriter.exe.
- 4. **MetricsReader.exe**: This executable is responsible for reading the output parameter from the Metrics.xml file generated after each simulation and logging it to the results file. Users the Script.txt file to determine which parameter to read from the Metrics file. If multiple parameters are to be read and logged, then the MetricsReader.exe can be called multiple times with Script.txt file having information about the parameter to be read each time.



- 5. **Supporting DLL's**: Some the supporting files such as ConfigWriter.dll, MetricsReader.dll, NetSimMetricsReader.dll, NetSimXmlReader.dll, etc. which are present in the project folder are used by other executable such as ConfigWriter.exe and MetricsReader.exe for various purposes during a multi-parameter sweep.
- 6. **runTest** script files: The files runTest.bat, runTest.py are the main script files that can be used to start a multi-parameter sweep process. Both files differ in the programming language used for the script.

runTest.bat uses Windows commands that can be executed by the windows command line interpreter. Batch scripts may get complex as the number of input and output parameters increases.

runTest.py uses python programming language which is less complex and offers more flexibility as the number of input and output parameters increases.


Users can also write the script to run the multi-parameter sweep process in a preferred programming language as per the convenience.

The script runs multiple simulation iterations based on the number of parameters to be varied and the range of values of each parameter.

Running a Multi-Parameter Sweep process:

Example 1: Modifying a single input parameter and logging a single output parameter

Consider the following network 5G network scenario in NetSim, comprising of a Wired Node, Router, gNB and a UE.




The network configuration has the initial distance between the gNB and UE as 50 meters with the gNB located at (1000,200) and UE located at (1000,250).

Multi-Parameter Sweeper is configured to run simulations for different distance between the gNB and UE by varying the UE Y coordinate value from 250 to 400 in steps of 50 meters.


1. The network scenario is saved and the content of the Configuration.netsim file is copied to the Multi-Parameter-Sweeper directory and renamed as input.xml.

Refer to the Example 1 directory which is part of the project folder (Multi-Parameter-Sweeper_v13.0\Examples\Multi-Parameter-Sweeper-Example-1)



The value of the Y coordinate of UE that is to be modified during each simulation run is updated ("{0}") in the configuration file as shown below:

2. The Script.txt file is updated with the details of the output parameter to be read from the Metrics.xml file and added to the result csv log file. In this case the Application throughput is to be logged for each simulation run.




3. runTest.py/runTest.bat is updated to pass the Y coordinate value during each iteration to generate Configuration file run simulation and update the result csv log.

The runTest.bat batch script modified for running simulations for different values of Y coordinates starting from 250 up to 400 in steps of 50 is shown below:


- NETSIM_PATH variable is set to the path of NetSim 32-bit/64-bit binaries in the install directory or workspace in the system.
- A result.csv file is created and added with headings Y and Throughput(Mbps)
- For loop is set to iteratively run simulations for values starting from 250 to 400 in steps of 50.
- The value of the parameter Y in the current iteration is written to the result log file for analysis.
- The value of the parameter Y in the current iteration is passed as input to ConfigWriter executable to generate Configuration.netsim file for each simulation.
- NetSim simulation is run via CLI mode by passing the apppath, iopath and license server information

• Configuration file and Metrics file are copied and renamed appending the value of the parameter in the current iteration.

The runTest.py python script modified for running simulations for different values of Y coordinates starting from 250 up to 400 in steps of 50 is shown below:



- NETSIM_PATH variable is set to the path of NetSim 32-bit/64-bit binaries in the install directory or workspace in the system.
- A result.csv file is created and added with headings Y and Throughput(Mbps)



- For loop is set to iteratively run simulations for values starting from 250 to 400 in steps of 50.
- The value of the parameter Y in the current iteration is passed as input to ConfigWriter executable to generate Configuration.netsim file for each simulation.

- NetSim simulation is run via CLI mode by passing the apppath, iopath and license server information.
- The value of the parameter Y in the current iteration is written to the result log file for analysis.

```
#Update the output Metric as crash if Metrics.xml file is missing

[csvfile.write('\n'+str(i)+','+'crash'+',')]

83

#Create a copy of the Configuration.netsim file appending the value of the variable parameters used in the current iteration if(os.path.isfile("Configuration.netsim")):

88

89

#Create a copy of the Metrics.xml file appending the value of the variable parameters used in the current iteration if(os.path.isfile("Metrics.xml")):

#Create a copy of the Metrics.xml file appending the value of the variable parameters used in the current iteration if(os.path.isfile("Metrics.xml")):

#Delete Configuration.netsim file appending the value of the variable parameters used in the current iteration if(os.path.isfile("Metrics.xml")):

#Delete Configuration.netsim file created during the last iteration if(os.path.isfile("Gonfiguration.netsim")):

#Delete Metrics.xml file created during the last iteration if(os.path.isfile("Metrics.xml")):

#Delete Metrics.xml file created during the last iteration if(os.path.isfile("Metrics.xml")):
```

- Configuration file and Metrics file are copied and renamed appending the value of the parameter in the current iteration.
- 4. Multi-Parameter Sweeping process is started by opening command prompt in the directory of the Multi-Parameter-Sweeping project and starting the batch script or the python script as shown below:

Batch Script:




Python Script:




This starts the Multi-Parameter-Sweeping process which runs NetSim simulations iteratively for different values of Y parameter of UE.


At the end of the process the Multi-Parameter-Sweeping folder will have the following file and folders created:



 Data: The Data directory contains the Configuration.netsim and the Metrics.xml files associated with each simulation run, renamed including the value of the parameter in the file name.



- **IOPath**: Used for storing the Configuration.netsim file and the simulation files generated during each simulation run.
- **Result.csv**: This is the output log which contains the parameter varied during each simulation run and the output parameter associated with each run.



Varying multiple network parameters:


In order to vary multiple network parameters during the multi-parameter sweep process each parameter in the input.xml file can be modified as {0},{1},{2},{3},.....{n} respectively.

Logging multiple output parameters:

Each output parameter that is to be logged should be part of the Script.txt file. However, the Script.txt file should contain only the details of one output parameter during the call to MetricsReader.exe.

To log multiple parameters, MetricsReader.exe can be called multiple times with Script.txt file having information about different parameter during each call.


For Example, there can be two Script files as shown below:



During each call to MetricsReader each of the Script files (Script1.txt and Script2.txt) can be renamed to Script.txt and renamed back.

Example 2: Modifying multiple input parameters and logging multiple output parameter

Consider the following network 5G network scenario in NetSim, comprising of a Wired Node, Router, gNB and a UE.



Properties configured in the LTE_NR interface of the gNB is shown in the table below:

Interface(5G_RAN) Properties	
Tx_Power(dBM)	40
Tx_Antenna_Count	8
Rx_Antenna_Count	4
CA_Type	Single Band
CA_Configuration	n78
CA_Count	1
MU	0
Channel Bandwidth (MHz)	10
PRB Count	52
MCS Table	QAM64
CQI Table	Table 1
X_Overhead	XOH0
DL UL Ratio	4:1
Outdoor Scenario	Rural Macro
LOS Mode	Standard
Wireless Link Properties	
Channel Characteristics	No_Pathloss
Wired Link Properties	
Link Speed (Mbps)	10000
BER	0
Propagation Delay (µs)	0
Application Properties	
Packet Size (Byte)	1460
Inter Arrival Time (µs)	166
Generation Rate (Mbps)	100

Transport Control	UDP
Start Time (s)	1
QoS	BE
Simulation Parameters	
Simulation Time (s)	1.1

Traffic is generated at a rate of 70 Mbps and upon running simulation, the throughput achieved is 59.95 Mbps.

We now find the max throughput for each possible bandwidth; Tx Antenna count and Rx Antenna count combination varying the generation rate based accordingly.

Two more parameters to be taken care include, the PRB Count and Guard Band (KHz) which vary with respect to the bandwidth.

Input Variables	Value Range
Channel Bandwidth (MHz)	10,15,20,25,30,40,50
Tx_Antenna_Count	1,2,4,8,16,32,64,128
Rx_Antenna_Count	1,2,4,8,16
PRB Count	52,79,106,133,160,216,270
Guard Band (KHz)	312.5,382.5,452.5,522.5,592.5,552.5,692.5
Reference Inter Arrival Time (Micro Seconds)	166
Reference Bandwidth	10
Reference DL MIMO Layer Count	2


Inter Arrival Time for each case is calculated based on the Reference IAT Bandwidth and DL MIMO Layer Count as shown below:

$$Inter\ Arrival\ Time\ (Micro\ Seconds) = \frac{Ref\ IAT}{\left(\frac{Curr\ BW}{Ref\ BW}\right)*\left(\frac{Curr\ DL\ MIMO\ Count}{Ref\ DL\ MIMO\ Count}\right)}$$

For E.g. In case of Bandwidth of 20 MHz and DL MIMO Count of 4 inter arrival time is


Inter Arrival Time (Micro Seconds) =
$$\frac{166}{\left(\frac{20}{10}\right)*\left(\frac{4}{2}\right)}$$
 = 41.5 Mbps

- 1. The network scenario is saved and the content of the Configuration.netsim file is copied to the Multi-Parameter-Sweeper directory and renamed as input.xml.
- 2. Refer to the Example 2 directory which is part of the project folder (Multi-Parameter-Sweeper_v13.0\Examples\Multi-Parameter-Sweeper-Example-2)




3. In the Input.xml file the value of the input variables are modified as shown in the table below:

Input Variables	
Channel Bandwidth (MHz)	{0}
Tx Antenna Count	{1}
Rx Antenna Count	{2}
Inter Arrival Time (Micro Seconds)	{3}
PRB Count	{4}
Guard Band (KHz)	{5}




4. The python script runTest.py is modified to run simulation for all possible combinations of Bandwidth and Tx Antenna Count and Rx Antenna Count with the respective values of Guard Band, PRB Count and the IAT that is calculated.




 Multiple parameters are read from the Metrics.xml file and logged in the results.csv file along with the input parameters such as CHANNELBANDWIDTH_MHz, TX_ANTENNA_COUNT, RX_ANTENNA_COUNT, INTER_ARRIVAL_TIME (micro sec)


Output Parameters Throughput(Mbps) Data Packets transmitted

6. Two script text files namely Script1.txt and Script2.txt are created with information to read each of the parameters from the Metrics.xml file.





7. In the python script runTest.py, MetricsReader is called twice, once to log each parameter by renaming the script files to Script.txt and back to its original name and separating the entries with a comma (","). The input parameters that were varied during each simulation run are also logged in the results.csv file.



8. The Input Configuration.netsim and the output Metrics.xml files associated with each simulation run is renamed including the bandwidth and DL MIMO count values that were used during each simulation run.


```
| The first plane | Date | Dat
```

5. Multi-Parameter Sweeping process is started by opening command prompt in the directory of the Multi-Parameter-Sweeping project and starting the python script as shown below:


Python Script:

This starts the Multi-Parameter-Sweeping process which runs NetSim simulations iteratively for different combinations of input parameters.

At the end of the process the Multi-Parameter-Sweeping folder will have the following file and folders created:



 Data: The Data directory contains the Configuration.netsim and the Metrics.xml files associated with each simulation run, renamed including the value of the parameter in the file name.



- **IOPath**: Used for storing the Configuration.netsim file and the simulation files generated during each simulation run.
- **Result.csv**: This is the output log which contains the parameter varied during each simulation run and the output parameter associated with each run.

