NetSim Multi-Parameter Sweep Program

Software Recommended:

NetSim v13.0 (32/64 bit), DOT NET CORE SDK 3.1, Python 3.7.4

Project Download Link:

https://github.com/NetSim-TETCOS/Multi-Parameter-Sweeper v13.0/archive/refs/heads/main.zip

Introduction:

When users want to *sweep* one or more parameters, they change their values between simulation runs, and compare and analyse the performance metrics from each run. NetSim multi-parameter sweeper enables users to automate the sweep process.


Consider an example, where a user wishes to create and simulate a network scenario for all possible values of one or more parameters in combination and analyse a set of performance metrics across the simulation runs. This is extremely time consuming to do manually using the NetSim GUI.

The multi-parameter sweep program enables users to automate the sweep process across multiple input parameters, simulate each run, save each result, and compare specific output metrics via a spreadsheet software like MS Excel.

The sweep program runs NetSim via its CLI interface.

File Organization

The project directory consists of several binaries which are responsible for different tasks during a multi-parameter sweep:



1. **input.xml**: This file contains the base NetSim network configuration that is to be simulated. This file is created by copy pasting the Configuration.netsim file that can be obtained by saving a network configuration in NetSim and renaming it to input.xml.

```
G - 🗇 📸 - 🚈 🖺 🚜 🦻 - 🤇
                                                                                               Live Share
         <?xml version="1.0" encoding="UTF-8" standalone="no"?>
       TETCOS_NETSIM xmlns:ns0="http://www.w3.org/2001/XMLSchema-instance" ns0:noNamespaceSchema
           <EXPERIMENT_INFORMATION>...</EXPERIMENT_INFORMATION>
           <GUI INFORMATION>...
           <NETWORK CONFIGURATION>
   19 E
             <DEVICE_CONFIGURATION DEVICE_COUNT="4">
               CDEVICE DEFAULT_DEVICE_NAME="gNB" DEVICE_ID="1" DEVICE_IMAGE="gNB.png" DEVICE_NAME

KDEVICE DEFAULT_DEVICE_NAME="EPC" DEVICE_ID="2" DEVICE_IMAGE="EPC.png" DEVICE_NAME
                                                                           DEVICE_IMAGE="WiredNode.png"
             </DEVICE CONFIGURATION>
               KLINK DEVICE_COUNT="2" LINK_COLOR="" LINK ID="1" LINK MODE="FULL DUPLEX"_LINK NAME
                KLINK DEVICE COUNT="2" LINK COLOR="" LINK ID="2" LINK MODE="FULL DUPLEX" LINK NAME
                KLINK DEVICE
             <APPLICATION_CONFIGURATION COUNT="1">
               KAPPLICATION APPLICATION COLOR=
                                                  "0x9000ffff" APPLICATION METHOD="UNICAST" APPLICATION
             </APPLICATION CONFIGURATION>
```

The values of parameters which are to be varied during each simulation run needs to be specified as {0}, {1}, {2}, etc. respectively.

For Example, if the X and Y coordinates of a device is to be varied the values can be modified in the input.xml file as shown below:

```
☑ <u>F</u>ile <u>E</u>dit <u>V</u>iew <u>P</u>roject <u>D</u>ebug <u>X</u>ML
          <?xml version="1.0" encoding="UTF-8" standalone="no"?>
        ☐<TETCOS_NETSIM xmlns:ns0="http://www.w3.org/2001/XMLSchema-instance" ns0:noNamespaceSchema
            <EXPERIMENT_INFORMATION>...</EXPERIMENT_INFORMATION>
            <GUI_INFORMATION>...
             <NETWORK_CONFIGURATION>
              <DEVICE_CONFIGURATION DEVICE_COUNT="4">
    19
                 kDEVICE DEFAULT_DEVICE_NAME="gNB" DEVICE_ID="1" DEVICE_IMAGE="gNB.png" DEVICE_NAME
                                                                             _IMAGE=
                 <DEVICE DEFAULT DEVICE NAME="EPC" DEVICE ID="2" DEVICE
<DEVICE DEFAULT DEVICE NAME="Wired Node" DEVICE ID="3"</pre>
                                                                             _IMAGE="EPC.png" DEVICE_NAM
DEVICE IMAGE="WiredNode.pn
                 <DEVICE DEFAULT DEVICE NAME="UE" DEVICE ID="4" DEVICE_IMAGE="UserEquipment.png" DEVI</pre>
                         3D X_OR_LON="{0}" Y_OR_LAT="{1}" Z="0">
                     <MOBILITY MODEL="NO_MOBILITY"/</pre>
                   </POS 3D>
                   <INTERFACE ID="1" INTERFACE_TYPE="LTE_NR">
                     <LAYER TYPE="NETWORK LAYER">
                       <NETWORK_PROTOCOL NAME="IPV4" SETPROPERTY="TRUE">
                         <PROTOCOL_PROPERTY DEFAULT_GATEWAY="11.2.1.1" IP_ADDRESS="11.2.1.2" SUBNET_M</pre>
        CRLF
```

2. **Script.txt:** This file should be updated with the parameter from the output metrics of NetSim that is to be logged at the end of each simulation run for the purpose of analysis.

At the end of every simulation, NetSim generates a Metrics.xml file which contain the performance metrics written in a specific format based on which it is loaded in the results dashboard.

Each Metric is part of a results table which can be accessed using a menu in the results dashboard.

A NetSim Metrics.xml file is shown below:

```
★ File Edit View Project Debug XML Test A<u>n</u>alyze Tools Extensions <u>W</u>indow <u>H</u>elp
G - O 📸 - 🖆 🖺 🤧 🤊 - C
                                                                      ▶ Attach... - | 👼 | 🚳 _
          MENU Name="Application_Metrics">
               <TABLE name="Application_Metrics">
               <TH name="Application Id" isShow="true"/>
<TH name="Throughput Plot" isShow="true"/>
                <TH name="Application Name" isShow="true"/>
<TH name="Source Id" isShow="false"/>
                <TH name="Destination Id" isShow="false"/>
                <TH name="Packet generated" isShow="true"</pre>
                <TH name="Payload generated (bytes)" isShow="false"/>
<TH name="Payload received (bytes)" isShow="false"/>
<TH name="Throughput (Mbps)" isShow="true"/>
                <TH name="Delay(microsec)" isShow="true"/>
<TH name="Jitter(microsec)" isShow="true"/>
                 <TC Value="1"/>
                   <TC Value="App1_CBR"/>
                  <TC Value="3"
                  <TC Value="25000"
                  <TC Value="36500000"/>
<TC Value="26201160"/>
```


For Example, if the application throughput is to be logged for each simulation run then the scrip file can be updated as shown below:



3. **ConfigWriter.exe**: This executable takes one or more command line arguments as input and generated Configuration.netsim file by replacing the arguments in place of the variable parameters specified in the input.xml file.

If there are two variable parameters specified in the input.xml file ({0} and {1}) then two arguments need to be passed while calling ConfigWriter.exe.

4. **MetricsReader.exe**: This executable is responsible for reading the output parameter from the Metrics.xml file generated after each simulation and logging it to the results file. Users the Script.txt file to determine which parameter to read from the Metrics file. If multiple parameters are to be read and logged, then the MetricsReader.exe can be called multiple times with Script.txt file having information about the parameter to be read each time.



- 5. **Supporting DLL's**: Some the supporting files such as ConfigWriter.dll, MetricsReader.dll, NetSimMetricsReader.dll, NetSimXmlReader.dll, etc. which are present in the project folder are used by other executable such as ConfigWriter.exe and MetricsReader.exe for various purposes during a multi-parameter sweep.
- 6. **runTest.py** uses python programming language which is less complex and offers more flexibility as the number of input and output parameters increases.

Users can also write the script to run the multi-parameter sweep process in a preferred programming language as per the convenience.

The script can be configured to run multiple simulation iterations based on the number of parameters to be varied and the range of values of each parameter.

NETSIM_PATH variable can be set to the path of NetSim 32-bit/64-bit binaries in the install directory or workspace which is to be used to run Simulations.

```
File Edit View Git Project Debug Test Analyze Tools Extensions Window Help Search (Ctrl+Q)
                                                                                                                                                                      ø ×
                                                          - ▶ Attach... - | ♬ | @ ; | 늘 师 | 표 2 | ■ 해 해 제 ;
6 - 0 | t3 - t≥ ■ ₽ | 9 - C - |

∠ Live Share

              import random
import shutil
import math
import sys
import os
                #Set the path of NetSim Binaries to be used for simulation. Either 32 bit or 64 bit
              NETSIM_PATH="C:\\Users\\HP\\Documents\\NetSim_13.0.26_64_std_default\\bin\\bin_x64"
              #Set NETSIM_AUTO environment variable to avoid keyboard interrupt at the end of each simulation os.environ['NETSIM_AUTO'] = '1'
               #Create IOPath directory to store the input Configuration.netsim file and the simulation output files during each iteration
         14 Dif not os.path.exists('IOPath'):
15 os.makedirs('IOPath')
               #Create Data directory to store the Configuration.netsim and the Metrics.xml files associated with each iteration
         21 #Clear the IOPath folder if it has any files created during previous multi-parameter sweep runs 22 = for root, dirs, files in os.walk('IOPath'):
23 = for file in files:
                        os.remove(os.path.join(root, file))
              #Clear the Data folder if it has any files created during previous multi-parameter sweep runs

⊡for root, dirs, files in os.walk('Data'):

⊘NoisustGund
```

For example,

64-bit:

NETSIM_PATH="C:\\Users\\HP\\Documents\\NetSim_13.0.26_64_std_default\\bin\\bin_x64"

32-bit:

NETSIM_PATH="C:\\Users\\HP\\Documents\\NetSim_13.0.26_32_std_default\\bin\\bin_x86"

license information> - License server details or the path of license file in case of node locked or cloud licenses

```
File Edit View Git Project Debug Test Analyze Tools Extensions Window Help Search (Ctrl+Q)
                                                                                                                                                                                                               - ø ×
                                                                       ☑ Live Share 🕏
                         if(os.path.isfile("IOPath\Metrics.xml")):
            51
52
                                os.remove("IOPath\Metrics.xml")
           53
54
55
56
57
58
59
60
61
62
63
64
65
66
67
72
73
74
75
                          \begin{tabular}{ll} \#Call ConfigWriter.exe with arguments as per the number of variable parameters in the input.xml file cmd='ConfigWriter.exe' '+str(i)' \\ \end{tabular} 
                          print(cmd)
                         os.system(cmd)
                         #Copy the Configuration.netsim file generated by ConfigWriter.exe to IOPath directory
if(os.path.isfile("Configuration.netsim")):
    shutil.copy("Configuration.netsim","IOPath\Configuration.netsim")
                       #Run NetSim via CLI mode by passing the apppath iopath and license information to the NetSimCore.ex cmd=NETSIM_PATH+"\\NetSimcore.exe -apppath "+NETSIM_PATH+" -iopath IOPath -license 5053@127.0.0.1"
                         #print(cmd)
                         #Create a copy of the output Metrics.xml file for writing the result log
if(os.path.isfile("IOPath\Metrics.xml")):
    shutil.copy("IOPath\Metrics.xml","Metrics.xml")
                          #Number of Script files i.e Number of Output parameters to be read from Metrics.xml
                          #If only one output parameter is to be read only one Script text file with name Script.txt to be provided
                         #If more than one output parameter is to be read only one script text file with name Script.txt to be provided
#If more than one output parameter is to be read, multiple Script text file with name Script1.txt, Script2.txt,...
#...,Scriptn.txt to be provided
OUTPUT_PARAM_COUNT=1;
```

For Example,

Server based license (<port no>@<server ip address>):

cmd=NETSIM_PATH+"\NetSimcore.exe -apppath "+NETSIM_PATH+" -iopath IOPath - license 5053@192.168.0.9"


Node Locked or Cloud licenses (path of license file):

cmd=NETSIM_PATH+"\\NetSimcore.exe -apppath "+NETSIM_PATH+" -iopath IOPath - license "+"\"C:\\Program Files\\NetSim\\Standard_v13_0\\bin\""

Running a Multi-Parameter Sweep process:

Example 1: Modifying a single input parameter and logging a single output parameter

Consider the following network 5G network scenario in NetSim, comprising of a Wired Node, Router, gNB and a UE.




The network configuration has the initial distance between the gNB and UE as 50 meters with the gNB located at (1000,200) and UE located at (1000,250).

Multi-Parameter Sweeper is configured to run simulations for different distance between the gNB and UE by varying the UE Y coordinate value from 250 to 400 in steps of 50 meters.

1. The network scenario is saved and the content of the Configuration.netsim file is copied to the Multi-Parameter-Sweeper directory and renamed as input.xml.

Refer to the Example 1 directory which is part of the project folder (Multi-Parameter-Sweeper_v13.0\Examples\Multi-Parameter-Sweeper-Example-1)



The value of the Y coordinate of UE that is to be modified during each simulation run is updated ("{0}") in the configuration file as shown below:

2. The Script.txt file is updated with the details of the output parameter to be read from the Metrics.xml file and added to the result csv log file. In this case the Application throughput is to be logged for each simulation run.



3. runTest.py is updated to pass the Y coordinate value during each iteration to generate Configuration file run simulation and update the result csv log.

The runTest.bat batch script modified for running simulations for different values of Y coordinates starting from 250 up to 400 in steps of 50 is shown below:

- A result.csv file is created and added with headings Y and Throughput(Mbps)
- For loop is set to iteratively run simulations for values starting from 250 to 400 in steps of 50.
- The value of the parameter Y in the current iteration is written to the result log file for analysis.
- The value of the parameter Y in the current iteration is passed as input to ConfigWriter executable to generate Configuration.netsim file for each simulation.
- NetSim simulation is run via CLI mode by passing the apppath, iopath and license server information
- Configuration file and Metrics file are copied and renamed appending the value of the parameter in the current iteration.

The runTest.py python script modified for running simulations for different values of Y coordinates starting from 250 up to 400 in steps of 50 is shown below:

```
| Possible | Edit View Git Project Debug Test Analyze Tools Estensions Window Help | Search (Chir-C) | Possible | Possibl
```

- NETSIM_PATH variable is set to the path of NetSim 32-bit/64-bit binaries in the install directory or workspace in the system.
- A result.csv file is created and added with headings Y and Throughput(Mbps)

```
| Solution | Solution
```

- For loop is set to iteratively run simulations for values starting from 250 to 400 in steps of 50.
- The value of the parameter Y in the current iteration is passed as input to ConfigWriter executable to generate Configuration.netsim file for each simulation.
- NetSim simulation is run via CLI mode by passing the apppath, iopath and license server information.


```
| Passet | Project | Debug | Rest | Apolyce | Book | Extensions | Window | Help | Search (Chif-C) | Passet | Pa
```

- The value of the parameter Y in the current iteration is written to the result log file for analysis.
- Configuration file and Metrics file are copied and renamed appending the value of the parameter in the current iteration.
- 4. Multi-Parameter Sweeping process is started by opening command prompt in the directory of the Multi-Parameter-Sweeping project and starting the python script as shown below:




This starts the Multi-Parameter-Sweeping process which runs NetSim simulations iteratively for different values of Y parameter of UE.


At the end of the process the Multi-Parameter-Sweeping folder will have the following file and folders created:




 Data: Contains multiple folders corresponding to each simulation run, with its name including the value of the parameters in that iteration.



 Each folder contains the all the output files associated with the simulation run.



- **IOPath**: Used for storing the Configuration.netsim file and the simulation files generated during each simulation run.
- **Result.csv**: This is the output log which contains the parameter varied during each simulation run and the output parameter associated with each run.



Varying multiple network parameters:

In order to vary multiple network parameters during the multi-parameter sweep process each parameter in the input.xml file can be modified as {0},{1},{2},{3},.....{n} respectively.

Logging multiple output parameters:

Each output parameter that is to be logged should be part of the Script.txt file. However, the Script.txt file should contain only the details of one output parameter during the call to MetricsReader.exe.


To log multiple parameters, multiple script files can be used. If n output parameters are to be logged, then there can be script1.txt, script2.txt,..., script.txt in the sweeper folder.

For Example, there can be two Script files as shown below:

Name	Date modified	Туре	Size
Data	05-06-2021 19:52	File folder	
IOPath	05-06-2021 19:52	File folder	
ConfigWriter.dll	10-04-2021 23:20	Application exten	5 KB
■ ConfigWriter.exe	10-04-2021 23:20	Application	171 KB
ConfigWriter.runtimeconfig.json	10-04-2021 23:20	JSON File	1 KB
🔝 input.xml	05-06-2021 15:48	XML Document	35 KB
MetricsReader.dll	10-04-2021 23:20	Application exten	5 KB
MetricsReader.exe	10-04-2021 23:20	Application	171 KB
MetricsReader.runtimeconfig.json	10-04-2021 23:20	JSON File	1 KB
NetSimMetricsReader.dll	10-04-2021 23:20	Application exten	10 KB
NetSimXmlReader.dll	10-04-2021 23:20	Application exten	5 KB
🗐 result.csv	05-06-2021 19:52	Microsoft Excel C	1 KB
📴 runTest.py	05-06-2021 16:48	Python File	5 KB
Script1.txt	10-04-2021 23:20	Text Document	1 KB
Script2.txt	10-04-2021 23:20	Text Document	1 KB

Example 2: Modifying multiple input parameters and logging multiple output parameter

Consider the following network 5G network scenario in NetSim, comprising of a Wired Node, Router, gNB and a UE.



Properties configured in the LTE_NR interface of the gNB is shown in the table below:

Interface(5G_RAN) Properties	
Tx_Power(dBM)	40
Tx_Antenna_Count	8
Rx_Antenna_Count	4
CA_Type	Single Band

70
n78
1
0
10
52
QAM64
Table 1
XOH0
4:1
Rural Macro
Standard
No_Pathloss
10000
0
0
1460
166
100
UDP
1
BE
1.1

Traffic is generated at a rate of 70 Mbps and upon running simulation, the throughput achieved is 59.95 Mbps.

We now find the max throughput for each possible bandwidth; Tx Antenna count and Rx Antenna count combination varying the generation rate based accordingly.

Two more parameters to be taken care include, the PRB Count and Guard Band (KHz) which vary with respect to the bandwidth.

Input Variables	Value Range
Channel Bandwidth (MHz)	10,15,20,25,30,40,50
Tx_Antenna_Count	1,2,4,8,16,32,64,128
Rx_Antenna_Count	1,2,4,8,16
PRB Count	52,79,106,133,160,216,270
Guard Band (KHz)	312.5,382.5,452.5,522.5,592.5,552.5,692.5
Reference Inter Arrival Time (Micro Seconds)	166
Reference Bandwidth	10
Reference DL MIMO Layer Count	2


Inter Arrival Time for each case is calculated based on the Reference IAT Bandwidth and DL MIMO Layer Count as shown below:

$$Inter Arrival \ Time \ (Micro \ Seconds) = \frac{Ref \ IAT}{\left(\frac{Curr \ BW}{Ref \ BW}\right) * \left(\frac{Curr \ DL \ MIMO \ Count}{Ref \ DL \ MIMO \ Count}\right)}$$

For E.g. In case of Bandwidth of 20 MHz and DL MIMO Count of 4 inter arrival time is

Inter Arrival Time (Micro Seconds) =
$$\frac{166}{\left(\frac{20}{10}\right)*\left(\frac{4}{2}\right)}$$
 = 41.5 Mbps

- 1. The network scenario is saved and the content of the Configuration.netsim file is copied to the Multi-Parameter-Sweeper directory and renamed as input.xml.
- 2. Refer to the Example 2 directory which is part of the project folder (Multi-Parameter-Sweeper_v13.0\Examples\Multi-Parameter-Sweeper-Example-2)




3. In the Input.xml file the value of the input variables are modified as shown in the table below:

Input Variables	
Channel Bandwidth (MHz)	{0}
Tx Antenna Count	{1}
Rx Antenna Count	{2}
Inter Arrival Time (Micro Seconds)	{3}
PRB Count	{4}
Guard Band (KHz)	{5}


4. The python script runTest.py is modified to run simulation for all possible combinations of Bandwidth and Tx Antenna Count and Rx Antenna Count with the respective values of Guard Band, PRB Count and the IAT that is calculated.

```
| Description |
```

 Multiple parameters are read from the Metrics.xml file and logged in the results.csv file along with the input parameters such as CHANNELBANDWIDTH_MHz, TX_ANTENNA_COUNT, RX_ANTENNA_COUNT, INTER_ARRIVAL_TIME (micro sec).




 Two script text files namely Script1.txt and Script2.txt are created with information to read each of the parameters from the Metrics.xml file. The variable OUTPUT_PARAM_COUNT is set to 2 as per the number of Script files. Script1.txt



7. In the python script runTest.py, MetricsReader is called to log each parameter specified in the script text files separating the entries with a comma (","). If simulation crashes, without generating the output Metrics.xml, then "crash" message is written to the log for each output parameter. The input parameters that were varied during each simulation run are also logged in the results.csv file.

```
| Property | Property
```

8. The simulation Configuration file and all the output files associated with each simulation run is saved to folders with name including the bandwidth and DL MIMO count values that were used during each simulation run.




5. Multi-Parameter Sweeping process is started by opening command prompt in the directory of the Multi-Parameter-Sweeping project and starting the python script as shown below:


Python Script:

This starts the Multi-Parameter-Sweeping process which runs NetSim simulations iteratively for different combinations of input parameters.

At the end of the process the Multi-Parameter-Sweeping folder will have the following file and folders created:



9. **Data**: The Data directory contains multiple output folders with the output files associated with each simulation run.



• **IOPath**: Used for storing the Configuration.netsim file and the simulation files generated during each simulation run.

• **Result.csv**: This is the output log which contains the parameter varied during each simulation run and the output parameter associated with each run.

