# HYPOSAT 6.2 and HYPOMOD 2.2 – The User Manual

Johannes Schweitzer

ORID: 0000-0002-5986-1492





# **Table of Contents**

1	INTRODUCTION	2
2	THE hyposat-in FILE	5
3	THE hyposat-parameter FILE	8
	3.1 GENERAL FORMATTING RULES	
	3.2 SEISMIC VELOCITY MODELS – TRAVEL-TIME TABLES	10
	3.2.1 Global Models	10
	3.2.2 Local or Regional Velocity Models	12
	3.2.3 Group Velocities	15
	3.2.4 Model Uncertainties	15
	3.3 STATION RELATED PARAMETERS	17
	3.4 SOURCE RELATED PARAMETERS	21
	3.4.1 Initial Source Time	21
	3.4.2 Initial Epicenter Estimation	22
	Latitude	23
	Longitude	23
	3.4.3 Initial Source Depth	24
	3.5 STEERING THE USAGE OF OBSERVATIONS	27
	3.5.1 Onset Time Observations and Phase Names	27
	3.5.2 Surface Reflections in the Case of a Water Layer on Top of the Model	29
	3.5.3 Other Non-traditional Phase Onsets	30
	3.5.4 Backazimuth (BAZ) Observations	30
	3.5.5 Slowness Observations	31
	3.5.6 Other Settings for Input Data	32
	3.6 The Inversion Process Steering Parameters	
	3.7 MAGNITUDE CALCULATION PARAMETERS	36
	3.8 I/O RELATED PARAMETERS	38
	3.8.1 Input	38
	3.8.2 Specific Parameters for ISF 1.0-formatted Input Files	38
	3.8.3 Output	40
	3.9 LIST OF OBSOLETE PARAMETERS AND THEIR NEW NAMES	45
4	THE hyposat-out FILE	46
5	THE PROGRAM HYPOMOD AND THE hypomod-out FILE	49
6	REFERENCES	52
7	INDEX	55

# Acknowledgments

I thank Myrto Pirli, Annie Jerkins, Andreas Köhler, Håkan Bolin, Celso Alvizuri and Bettina Goertz-Allmann for checking consistency and clarity of this Manual and suggesting additions and corrections.

### 1 INTRODUCTION

**HYPOSAT** is a program developed to locate single seismic sources and **HYPOMOD** is a program to calculate residuals of observed data for a given seismic source location. Both programs utilize observed onset time, backazimuth (*i.e.*, station-to-event azimuth, BAZ) and ray-parameter observations. Additionally, all possible travel-time differences between different onsets at individual stations can be included in the location process (*e.g.*, the onset-time difference between the phases PcP and P ( $t_{PcP} - t_P$ ) gives additional constraint for the source depth). If amplitude and period measurements are available for P or S onsets or for surface waves, individual station and network magnitudes can also be estimated. The files *HYPOSAT\_HISTORY.md* and *HYPOMOD\_HISTORY.md*, which are part of the program documentation, contain listings of the program versions and main changes from version to version.

For clarity, all file names in this Manual are written in bold *italics*. This document and all **HYPOSAT / HYPOMOD** output are consequently using the phrases 'location uncertainty', 'model uncertainty' and 'data uncertainty' instead of 'location error', 'model error' and 'data error' and it is clearly distinguished between the terms 'backazimuth' and 'azimuth', where backazimuth (BAZ) is used for defining the direction from the station to the epicenter measured from North clockwise over East in [°].

Seismic phases considered in both programs are those included in IASPEI 1991-type travel-time tables. The program follows the seismic phase name convention as recommended by IASPEI on its General Assembly in Sapporo, in July 2003 (Storchak *et al.*, 2002; 2003; 2006; 2009; 2011; Bormann *et al.*, 2013; Schweitzer *et al.*, 2021a). A software package (*libtau*-software) for travel-time-table calculations for spherical Earth models is distributed with the IASPEI 1991 tables. It is based on the tau-spline algorithm (Bulland & Chapman, 1983) and was here implemented and modified such that all precalculated data files become platform independent ASCII files. In addition to the original software version, diffracted PKPbc and double surface reflections of body waves (*e.g.*, PPP or S'S'S'), depth phases for surface reflections (pPP & sSS, pP'P' *etc.*), depth phases of core reflections (pPcP, sScS), single surface reflections of core phases (PcPPcP & ScSScS) as well as S3KS were included in the travel-time-table calculations. Reflections from the Conrad discontinuity – in the following appreciated as 'the Conrad' – (PbP, SbS) or the Mohorovičić discontinuity – in the following appreciated as 'the Moho' – (PmP, SmS), if local/regional seismic velocity models are used.

For most of the phases or their proxies, ellipticity corrections are automatically calculated with the adapted software of Kennett & Gudmundsson (1996). Instead of the original Kennett & Gudmundsson coefficients, the program uses the updated and corrected set of coefficients from Russell *et al.* (2022). However, note that for double surface reflections (*e.g.*, PgPgPg, SnSnSn, PPP, SSS, P'P'P' *etc.*), ellipticity corrections cannot be applied at this moment.

Since **HYPOSAT 6 / HYPOMOD 2** (see Schweitzer, 2018) the global crustal model with 5° x 5° resolution Crust 5.1 (Mooney *et al.*, 1998) has been replaced by the global crustal model with 1° x 1° resolution CRUST 1.0 (Laske *et al.*, 2013). With **HYPOSAT 6.1 / HYPOMOD 2.1**, the usage of CRUST 1.0 is extended: when requested, the program can now correct reflections at the Earth's surface not only for topography but also for the water-depth of oceans and larger

lakes (as far as defined in CRUST 1.0), for further details see Schweitzer (2025). With this change, pwP-type phases are now included, but the program will also correct all types of P- or S-phase reflections at the surface and may change the phase name accordingly. As an extension to the IASPEI phase-name convention (Storchak *et al.*, 2002; 2003; 2006; 2009; 2011; Bormann *et al.*, 2013; Schweitzer *et al.*, 2021a), **HYPOSAT / HYPOMOD** allow not only pP changing to pwP but also *e.g.*, PP to PwP or P'P' to P'wP').

HYPOSAT runs in an iterative mode, in which each iteration step is based on the solution of an equation system with the Generalized Matrix Inversion (GMI) (see *e.g.*, Bolt (1970) and Niewiadomski (1989) or the textbooks of Aki & Richards (1980) or Menke (1989)). All partial derivatives for the matrix inversion are recalculated before each iteration. After each iteration, the program evaluates the inversion results and either continues with another iteration step or stops all processing and generates an output with the location results. The user can steer this processing with different options for the usage of the input data and theoretical travel-time models and additional parameters for the inversion itself (see Chapter 3). More details about the program features can also be found in Schweitzer (1997; 2001; 2002; 2006; 2018; 2025), Schweitzer & Kennett (2007) and Schweitzer *et al.* (2021b).

For inverting a seismic event location, the program reads a set of ASCII-formatted input files. Two files are user defined input files. One file contains the observed data for the event to be localized (*hyposat-in*) and the other file contains a list of parameters to steer this inversion process (*hyposat-parameter*). The location results will be written in the file *hyposat-out*. The contents and structure of these files will be explained in the following three Chapters of this Manual. The program **HYPOMOD** (see for further details Chapter 5) uses the same input files as **HYPOSAT** but writes its results in the file *hypomod-out*.

In addition, there are a number of files containing static input data for the travel-time-table calculations in global spherical Earth models (e.g., iasp91\_A.tbl and iasp91\_A.hed), the ellipticity corrections (elcordir.tbl), all data defining the global crustal model CRUST 1.0 (crust1.vp, crust1.vs, crust1.bnds) of Laske et al. (2013), crustal models of the global models (std\_crusts.dat), attenuation corrections for magnitude estimations (MB\_G-R.DAT, MB\_V-C.DAT, MB\_M-R.DAT, MLCORR.TABLE, MLCORR.TBALE.wa, MLCORR.TABLE.nicolas), ISC default-depth definitions (isc\_def\_depth.dat, grn\_def\_depth.ak135.dat), the file with the geographic coordinates of the station stations.dat and a list of European seismo-tectonic units (REG\_L3.DAT, see e.g., Lindholm et al., 2000). These static files must be either located in the run-directory or in a common directory defined by the environment variable HYPOSAT\_DATA. For some files alternative directories can be set in hyposat-parameter; for further details see Chapter 3.

The newest version of **HYPOSAT** and **HYPOMOD** (including source code, this Manual, the PDF version of Schweitzer (1997), data files containing travel-time models and station parameters, and several examples) are available from GitHub for free download. The software is written in Fortran, C or C++ and was developed and tested with the GNU Compiler Collection (GCC) on LINUX PCs and Intel® compilers in a WINDOWS 10 and Windows 11 environment. For instructions on installing **HYPOSAT** and **HYPOMOD** on your computer, please consult the documentation on GitHub (https://github.com/NorwegianSeismicArray/Hyposat).

All older software-package versions are obsolete, as well as testing the implementation in a SUN (Solaris) environment are no longer supported. Be also aware, that the previous option to download the software package from NORSAR's anonymous FTP address *ftp.norsar.no* is no longer supported from version **HYPOSAT 6.1 / HYPOMOD 2.1** on.

Questions related to program updates and maintenance should be directed to the author.

# 2 THE hyposat-in FILE

**HYPOSAT** needs a file with all the observed data for a specific event: This file has by default the name *hyposat-in*, but another name can be defined in the parameter file *hyposat-parameter*. Be aware that the format of this file has slightly changed in **HYPOSAT 6**. If you have older formatted files, this must be indicated in the *hyposat-parameter* file. The data input file must have the following format:

1<sup>st</sup> line: any title for event identification of maximum 80 characters (used also in the output-file *hyposat-out*).

 $2^{nd}$  – to (n+1)'th line with the n-observed onsets. These lines **must** (!) be compatible with the following format (Fortran: 'a' is ASCII string, 'i' is integer number, 'f' is float number, 'x' is a separating blank space):

(a5,1x,a8,1x,i4,4(1x,i2),1x,f6.3,1x,f5.3,1x,f6.2,3(1x,f5.2),1x,a7,1x,f6.3,1x,f12.2,1x,f7.2,1x,a8,1 x,f5.2)

station id (a5), phase name (a8), year (i4), month (i2), day (i2), hour (i2), minute (i2), second (f6.3), standard deviation of the onset time (f5.3), backazimuth (BAZ) (f6.2), standard deviation of the BAZ observation (f5.2), either slowness or ray parameter [s/deg(ree) or s/°] or apparent velocity [km/s] (see the parameter setting with **SLOWNESS [S/DEG]** in the file *hyposat-parameter*) (f5.2) and standard deviation of the slowness observation in [s/°] or [km/s] (f5.2).

If the type of the P or S onset is unknown, you can use the phase names **P1** or **S1** to indicate that this is the 1<sup>st</sup> P-type or the 1<sup>st</sup> S-type onset at this station. Then, the program chooses the right phase name depending on the epicentral distance of the observation and the employed travel-time table.

Following the IASPEI standard, phases named tx(TX), rx(RX), x(X), Px(PX) or Sx(SX) are assumed to be unknown phase onsets. Then, onset time and slowness will not be included in the inversion. After the inversion, the program will search for the best fitting seismic phase and list it as used phase name.

For each phase name not defined by the applied travel-time model(s), the program searches for the best fitting phase. However, onset time and slowness or ray parameter of such a phase are not used in the inversion, but the BAZ information may be used if the parameter **USE ALL BAZ INFORMATION** is set in *hyposat-parameter*.

The input of the values for BAZ, slowness, amplitude and period are optional. If BAZ or slowness values are not available, these places can stay blank, or they must be set to '-999.' or '-1.'.

If an onset time, a BAZ, or a slowness value is given without its standard deviation, the following default values are used: onset time 2 s; BAZ 30° (40° for LQ and LR); slowness or ray parameter 5 s/° (any apparent velocity in [km/s] input will be internally converted to [s/°]).

Then follows a seven-character long combination of steering flags (a7). These seven steering flags (1234567) control the usage of the different onset parameters during the inversion and have the following meanings and options:

- Position 1 the time reading of this onset can be used ('T' or 't') or not used ('\_') for the inversion. The travel-time difference between S- and P-type onsets ( $t_S$   $t_P$ ) can be used for calculating an initial solution for the source time with the Wadati method (Wadati, 1932; 1933) and/or the epicentral distance from the corresponding station. For this Position 1 must have been set to 'T' or 't' for both onsets.
- Position 2 the BAZ reading of this onset can be used ('A' or 'a') or not used ('\_') for the inversion.
- Position **3** the slowness reading of this onset can be used (**'S'** or **'s'**) or not used (**'\_'**) for the inversion.
- Position 4 the time reading of this onset can be used ('D' or 'd') or not used ('\_') to calculate travel-time differences as input data for the inversion.
- Position 5 the onset time reading of this onset will be corrected ('R' or 'r') or not corrected ('\_') for the crustal structure below a reflection point at the Earth's surface by calculating the travel-time difference for the ray path through the crust in the used global model (as set with GLOBAL MODEL in hyposat-parameter) and in CRUST 1.0.
- Position 6 the amplitude and period readings of this onset can be used ('M' or 'm') or not used ('\_') for magnitude calculations. (Remark: the *hyposat-in* files in older format do not have this flag).
- Position 7 if set to '2', '3', or '4', other global, spherical Earth models (as set with GLOBAL MODEL 2, GLOBAL MODEL 3, or GLOBAL MODEL 4 in file hyposat-parameter) will be used to calculate the theoretical onset time, the slowness or ray parameter, and their partial derivatives for this onset. With any other character at this place, the standard global Earth model (see GLOBAL MODEL in file hyposat-parameter) will be used.

If keeping the positions  $\mathbf{1}-\mathbf{7}$  blank (' ') the flag combination **TASDRM**\_ will be automatically used as default value.

Then, one can add the following optional input data: the period of the observed onset (f6.3), the amplitude of the signal in [nm] (f12.2), the signal-to-noise ratio (SNR) (f7.2), an eight-character long arrival id (a8) and finally the 2<sup>nd</sup> standard deviation for the onset time reading (see also **DOUBLE SIDED TIME UNCERTAINTY** in *hyposat-parameter*) (f5.2).

The amplitude / period information is only used if both values are larger than 0.0.

All lines starting with 'STOP', a star '\*' or a blank space ' ' as well as identical lines following each other are ignored and not used.

When using the correct format, an input file may look like the example below:

------ end of the *hyposat-in* file example ------

### ------ example of a *hyposat-in* file ------NORTHERN MOLUCCA SEA, 1996 29 June, converted from pIDC's Reviewed Event Bulletin (REB) \* The row above is the title line \*23456789 123456 1996 06 29 00 45 48.7 0.600 338.0 20.0 17.0 1996 06 29 00 42 12.8 0.300 -999. 0.0 -999. OIS Р1 0.00 T\_D\_ 35.50 abcdef03 0.10 1996 06 29 00 45 44.8 0.300 PcP abcdef04 QIS T\_D 1.00 TASD M 1.00 TASD M 2.00 TASD M 2.00 TASD M 7.1 1996 06 29 00 42 16.9 1996 06 29 00 45 45.2 1996 06 29 00 46 45.3 0.300 346.3 20.0 3.40 2.20 3.90 35.10 abcdef05 0.500 ASAR 0.10 0.300 345.1 0.600 347.6 0.300 339.4 0.300 -999. ASAR PcP 20.0 2.3 0.500 11.50 abcdef06 6.10 abcdef07 ASAR 0.20 8.20 abcdef08 1996 06 29 00 42 31.2 1996 06 29 00 45 49.4 WARB 30.0 8.2 0.700 6.50 0.10 0.00 abcdef09 WARB PcP 0.0 T\_\_D\_\_ 0.300 -999. 0.0 0.300 109.7 30.0 1996 06 29 00 42 42.7 1996 06 29 00 43 09.0 1996 06 29 00 57 48.7 0.00 T 2.00 TAS M 0.400 2.00 A M 19.360 6 80 abcdef10 MEEK -999. 0 10 CMAR 0.60 LR 50.000 110.0 30.0 39.5 188.80 abcdef12 25.00 CMAR 10.80 abcdef13 FORT WOOL 1996 06 29 00 43 11.3 1996 06 29 00 43 15.6 0.300 0.10 2.00 TAS M 0.600 4.10 8.80 abcdef14 0.10 0.300 -999. 0.300 -999. 0.0 0.300 323.2 20.0 0.00 T\_\_\_\_\_\_ 1.00 TASD\_M\_\_\_\_ 0.600 -999. 9.0 SHK 1996 06 29 00 43 25 4 abcdef15 0 10 1996 06 29 00 43 46.8 7.20 8.30 abcdef16 10.00 T D 0.00 T D 0.000 T STKA PcP 1996 06 29 00 46 12.0 -999. 0.300 -999. 0.0 abcdef17 0.10 1.70 40.10 7.20 abcdef18 1996 06 29 00 43 46.7 1996 06 29 01 04 25.0 0.300 177.3 50.000 160.0 20.0 P LR abcdef19 25.00 KSAR P P 1996 06 29 00 43 51.9 1996 06 29 00 46 47.0 0.300 357.1 20.0 0.300 111.2 30.0 2.00 4.30 abcdef20 0.10 23.80 abcdef21 0.10 MJAR PDY -999. -999. 1996 06 29 00 47 09.0 1996 06 29 00 48 09.5 0.300 -999. 0.300 -999. 0.00 T\_\_\_\_\_ ZAL 0.0 abcdef22 ABKT \*NRI P 1996 06 29 00 48 08.7 0.300 195.9 30.0 3.9 2.00 TAS\_M\_ 0.750 3.00 11.20 abcdef24 0.10 \* Note, the following phase has an unknown phase name! Therefore, its onset time or slowness cannot be used \* for the inversion. However, the backazimuth observation may be usable. \* 2.00 A M 0.750 0.00 T 0.00 T 0.00 T NRI 1996 06 29 00 48 08.7 0.300 195.9 30.0 3.9 2.00 3.00 11.2 abcdef24 0.10 1996 06 29 00 49 01.1 1996 06 29 00 49 17.2 0.300 -999. 0.300 -999. MAW P KVAR P 0.0 -999. 0.0 -999. abcdef26 0.10 NPO P ARCES P 1996 06 29 00 49 31.0 1996 06 29 00 49 51.7 0.300 -999. 0.0 -999. 20.0 4.1 abcdef27 0.10 0.00 T 1.00 TAS M 0.550 2.00 TAS M 0.900 1.00 TAS M 0.550 2.00 TAS M 0.750 94.5 0.300 0.80 10.50 abcdef28 0.10 1996 06 29 00 49 55.9 1996 06 29 00 50 00.0 0.300 116.6 0.300 111.2 30.0 3.5 5.9 3.60 0.60 10.40 abcdef29 6.60 abcdef30 SPITS P 0.10 FINES P 1996 06 29 00 50 28.7 0.300 311.3 30.0 1.5 2.00 TAS M 1996 06 29 00 55 42.7 0.300 -999. 0.0 -999. 0.00 T 1996 06 29 00 55 41.2 0.300 -999. 0.0 -999. 0.00 T 1996 06 29 00 55 57.1 0.300 -999. 0.0 -999. 0.00 T 1996 06 29 00 56 09.1 0.300 311.9 30.0 6.4 2.00 TAS M 1996 06 29 00 56 44.7 0.300 -999. 0.0 -999. 0.00 T HFS 1.10 3.70 abcdef31 TXAR PKPdf SCHO PKPdf abcdef33 0.10 DBIC PKPdf abcdef34 0.10 PKPdf PLCA 0.900 4.40 abcdef35 LPAZ PKPdf abcdef36

# 3 THE hyposat-parameter FILE

The file *hyposat-parameter* contains the inversion-steering parameters and is read by both programs **HYPOSAT** and **HYPOMOD** (see Chapter 5). The file must be located either in the directory where the program is executed or in the directory as defined by the environment variable **HYPOSAT\_PARA**. For instructions on how to define environment parameters please consult the program-package-installation documentation on GitHub. If the parameter file has another name than *hyposat-parameter*, this name including its whole directory path name must be defined by the environment variable **HYPOSAT\_PARA**. This file is read only once at the beginning of a location run.

Several of the parameters are only applicable in special cases and without any effect in many others. They contribute to the customization abilities of the program for different applications and the user should check carefully what is really needed for their actual case and what can just be ignored or not set. See the examples in the directory <code>./examples/</code> and the file <code>hyposat-parameter\_all</code> in the <code>./man/</code> directory with all possible parameters listed together with their default settings.

HYPOSAT and HYPOMOD can read data either from files formatted in their own format or in the International Seismic Format (ISF 1.0) as defined by the Commission of Seismological Observation and Interpretation of IASPEI version ISF 1.0. This format is compatible with the format used by the International Monitoring System (IMS) of the Comprehensive Test-Ban-Treaty Organization (CTBTO) for its bulletins. HYPOSAT can also write the inversion results in ISF 1.0 and in JSON formatted output files. For the i/o of ISF formatted files an ISC-software package was adapted for the usage in HYPOSAT. Some parameter settings in the hyposat-parameter file are only related to i/o of ISF formatted files (see Chapter 3.8).

The syntax in the *hyposat-parameter* file has changed during the development of the different **HYPOSAT** versions. For compatibility reasons, the old syntax versions are still working and will be supported – at least for a while. All parameter settings in old syntax and their new equivalent entries are listed at the end of Chapter 3.

In the following all parameters and their possible settings are explained in detail. Mandatory and relevant parts of the parameter definitions are written in this document in **bold** and **capital characters**. An example is given in red with the default parameter setting. For running **HYPOSAT** with specific parameter settings, you can just copy the relevant lines from these examples and modify them as needed. See also the file **hyosat-parameter\_all**.

### 3.1 GENERAL FORMATTING RULES

Each parameter is defined in an extra line, starting with the mandatory parameter name, followed by a required colon (':'). After the mandatory colon follows one mandatory blank space (' ') and then the parameter setting itself. Leading blank spaces (' ') in a line will be ignored.

Be aware that since **HYPOSAT 6.2**, this **mandatory colon** has no longer to be located at the fixed position at character 36 in the line, but it **must** follow after the parameter name. However, all old **hyposat-parameter** files will still work as before.

Any blank line or lines with a star (\*) as 1st character are ignored.

Whenever a line does not comply with these rules, a warning message will be written when running the program and the setting in the line will be ignored.

The order in which the parameters are set is arbitrary. Each line can be repeated several times within the file with another setting. In this case, the last set value is applied for the location process. The total number of lines in the file is limited to 2000 lines.

All default values are set when starting the program. For file names, the full directory path name can be given with a maximum length of 512 characters.

### 3.2 SEISMIC VELOCITY MODELS – TRAVEL-TIME TABLES

### 3.2.1 Global Models

The parameter **GLOBAL MODEL** (or **GLOBAL MODEL 1**) defines the reference spherical velocity model used to calculate all travel-time related theoretical data. The **HYPOSAT 6.2** package contains data files for the following global models:

ak135_A	AK135 model (Kennett <i>et al.,</i> 1995)
ek137_A	EK137 model (Kennett, 2020)
iasp91_A	IASPEI 1991 model (Kennett, 1991; Kennett & Engdahl, 1991)
iasp91a_A	IASPEI 1991, with a corrected core model (Kennett, pers.
	communication)
jb_A	Jeffreys-Bullen model (Jeffreys & Bullen, 1940 and later)
prem_A	PREM model (Dziewonski & Anderson, 1981)
sp6_A	SP6 model (Morelli & Dziewonski, 1993)

Some additional, regional spherical Earth models with different crusts and uppermost mantle layers are also included in the **HYPOSAT** software package. From a depth of 220 km on, they are identical to the AK135 model:

barey_A	BAREY, regional model for the European Arctic (Schweitzer &						
	Kennett, 2007)						
barez_A	BAREZ, regional model for the European Arctic (Schweitzer &						
	Kennett, 2007)						
barents16_A	BARENTS16, regional model for the western Barents Sea (Pirli &						
	Schweitzer, 2017)						
bergen_A	University of Bergen's velocity model for Norway (Havskov &						
	Bungum, 1987)						
fescan_A	NORSAR's Fennoscandia model (Mykkeltveit & Ringdal, 1981)						

The directory, where these data files are located, must be specified with the environment variable HYPOSAT\_DATA before starting the program. The travel-time tables are calculated with the *libtau*-software package (Buland & Chapman, 1983), and originally distributed as IASPEI91-software, here with the extensions as described in the **Introduction**. To become computer architecture and operation system independent, all global travel-time models for the *libtau*-software were recalculated for the HYPOSAT package, stored in ASCII format and got the suffix 'A' in their table names. The default global model is 'ak135 A'

GLOBAL MODEL: ak135\_A

or alternatively:

GLOBAL MODEL 1: ak135\_A

One can give the name of any other  $2^{nd}$  global model to be used for specific ray paths as indicated in the data input file *hyposat-in*. Up to three additional spherical Earth models can be used for specific travel paths.

GLOBAL MODEL 2: ak135\_A

One can give the name of any other  $3^{rd}$  global model to be used for specific ray paths as indicated in the data input file *hyposat-in*.

GLOBAL MODEL 3: ak135 A

One can give the name of any other 4<sup>th</sup> global model to be used for specific ray paths as indicated in the data input file *hyposat-in*.

GLOBAL MODEL 4: ak135\_A

The seismic velocities in the crust must be known for the chosen dominant global model (set with the parameter **GLOBAL MODEL**), so that **HYPOSAT** can apply crustal travel-time corrections. The crustal structures of all prepared *libtau*-type models are collected in a file called **std\_crusts.dat** and marked with a unique code. This file must reside in the same directory as defined by the environment variable **HYPOSAT\_DATA**. **std\_crusts.dat** is included in the directory **./data/**. If you use another global model than AK135 as defined by **GLOBAL MODEL** (or **GLOBAL MODEL 1**), the program will automatically adjust this parameter. However, you can overwrite this setting and force the program to use a specific standard crust by setting the following parameter. The following different codes are possible:

- **E1** Jeffreys-Bullen (global standard model)
- **E2** PREM (global standard model)
- E3 IASPEI 1991 (global standard model)
- **E4** IASPEI 1991a (global standard model, with corrected core)
- **E5** SP6 (global standard model)
- **E6** AK135 (global standard model)
- **E7** FESCAN (regional standard model)
- **E8** BAREY (regional standard model)
- **E9** BAREZ (regional standard model)
- **EA** BARENTS16 (regional standard model)
- **EB** BERGEN (regional standard model)
- **EC** EK137 (global standard model)

By default, the standard code is 'E6' (for AK135).

**GLOBAL CRUSTAL MODEL CODE: E6** 

If using as input a *hyposat-in* formatted file (see Chapter 2), the usage of alternative spherical Earth models can be specified for specific observations. In the case of using an ISF-formatted input file this is not possible. In this case, one can define an epicentral distance in [°], from which **GLOBAL MODEL 2** should be used to calculate the theoretical onset times. However, be aware that the model usage may differ for some observations from iteration to iteration because of a change in the epicentral distance.

The default value is '999.', which means no usage of a 2<sup>nd</sup> velocity model in the case of an ISF formatted input file.

**ISF\_2ND MODEL DISTANCE: 999.** 

### 3.2.2 Local or Regional Velocity Models

**HYPOSAT** can combine global velocity models with an epicentral-distance-dependent **LOCAL OR REGIONAL MODEL**. The local/regional travel-time models are either used around the source and/or to calculate travel-time corrections for reflection points of phases at the Earth's surface or for crustal differences between the dominant global model and the actual structure at the stations (velocities & elevation). The input is a file containing the model parameters. The velocity model must contain the following information:

- In the 1<sup>st</sup> line maxdis = maximum distance in [°] for which this model shall be used.
- It is followed by lines with depth in [km], the P velocity (Vp) in [km/s], and the S velocity Vs in [km/s]. The model may contain layers with a constant velocity or with velocity gradients.
- First order discontinuities must be specified with two lines for the same depth.
- Additionally, the Conrad and the Moho must be marked as shown in the following example. Please note that the mark for the Conrad and the Moho must be in the 1<sup>st</sup> line defining the first order discontinuity. Without these discontinuity definitions, the program will name all calculated crustal and regional phases Pg (or Sg, respectively).

CRUST 1.0 defines the Moho but not the Conrad. Here **HYPOSAT** is setting the Conrad at the depth where the P-velocity  $Vp \ge 6.3$  [km/s].

All direct phases from sources below a depth of 210 km or with a ray path in a layer below this depth will be named P (or S, respectively) instead of Pn (Sn).

The maximum number of model layers is set to 100.

example for a file containing a regional velocityexample for a file containing a regional velocity							
10.				maxdis in free format			
0.000	5.400	3.100		depth, Vp, Vs in format (3F10.3)			
10.000	5.800	3.200					
20.000	5.800	3.200CONR		+ mark for the 'Conrad'			
20.000	6.500	3.600		in format (3F10.3,A4)			

30.0 30.0 77.5 120.0	000 500	8.100 8.050	'	+ mark for the 'Moho' in format (3F10.3,A4)	
	end	l of evample	 		

If the file containing this velocity model is not available in the run-directory or the directory defined by the environment variable **HYPOSAT\_DATA**, one must give the full file name including its directory path. Set it to '\_' if no local model is used.

### **LOCAL OR REGIONAL MODEL:**

Travel times will be calculated for the following seismic phases (as far as the ray theoretically exist with respect to distance and source depth):

- Direct and reflected P-phases: Pg, Pb, Pn, P, pPg, pPb, pPn, pP, PbP (i.e., in this program the upper side reflection from the Conrad), PmP, PgPg, PbPb, PnPn, PP, PgPgPg, PbPbPb, PnPnPn, PPP
- P-to-S converted phases: pSg, pSb, pSn, pS, PbS, PmS
- Direct and reflected S-phases: Sg, Sb, Sn, S, sSg, sSb, sSn, sS, SbS, SmS, SgSg, SbSb, SnSn, SS, SgSgSg, SbSbSb, SnSnSn, SSS
- S-to-P converted phases: sPg, sPb, sPn, sP, SbP, SmP

When using the local/regional model for calculating local/regional travel-time tables and their partial derivatives, one can define the seismic phase types to be considered by a 4-digit number code: The position of a digit defines the phase type and the value of the digit defines the action for this phase:

**dxxx** the digit (d) at the 1<sup>st</sup> position is the flag related to surface reflections (e.g., pP or sS).

xdxx the digit (d) at the 2<sup>nd</sup> position is the flag for surface multiples (e.g., PP, SS, PPP or SSS).

**xxdx** the digit (d) at the 3<sup>rd</sup> position is the flag for reflections at the Conrad or the Moho (*e.g.*, PbP or SmS). Note that here the name 'PbP' is used to indicate a reflection from the Conrad, which is not a regular phase name as recommended by IASPEI (Storchak *et al.*, 2002; 2003; 2006; 2009; 2011; Bormann *et al.*, 2013; Schweitzer *et al.*, 2021a).

**xxxd** the digit (d) at the 4<sup>th</sup> position is the flag for converted phases (e.g., sP or PmS).

The digit **d** itself can have the following values:

- 1 = only P-type onsets will be calculated
- **2** = only S-type onsets will be calculated
- **3** = both phase types (P and S) will be calculated

*E.g.*, the combination **1320** means the phases pP, PP, PPP, SS, SSS, SbS and SmS will be calculated, but none of the converted phases. The combination **0000** or simply **0** means only

the direct P- and S-onsets, but none of the reflected and/or converted phases will be calculated. For any value below **0**, the program will ignore the local/regional model set by **LOCAL OR REGIONAL MODEL**. The default value is set to '3333'.

### **PHASE INDEX FOR LOCAL MODEL: 3333**

The following setting is steering the usage of the 1° x 1° crustal model CRUST 1.0 of Laske et al. (2013) together with the other local/regional velocity models. The usage can be chosen by an integer number:

- <= 0 = no usage of CRUST 1.0 or any other local/regional model as defined with LOCAL OR REGIONAL MODEL (this is also the default value).
- 1 = only the local/regional model is used as defined in **LOCAL OR REGIONAL MODEL**. The model is also used for eventually correcting teleseismic travel times of near source reflections (depth phases) (pP, pwP, sS, sP, etc.).
- 2 = CRUST 1.0 is only used for calculating station corrections and for travel-time corrections for model differences at the reflection points of the phases (e.g., pP, sS, PnPn, sS, P'P' ...). Reflection point corrections cannot (!) be calculated for multiple reflections as e.g., pPP, SSS, etc., and if stations or reflection points are located within the maximum distance from the source as defined in LOCAL OR REGIONAL MODEL. Then, it is assumed that the LOCAL OR REGIONAL MODEL contains already the correct seismic velocities and no further corrections are needed.
- **3** = CRUST 1.0 is only used to calculate travel times to stations with a maximum distance of 1.5° from the source. **LOCAL OR REGIONAL MODEL** is not used.
- 4 = combines options (2) and (3).
- **5** = **LOCAL OR REGIONAL MODEL** is used for near source surface reflections (depth phases) and CRUST 1.0 is used for all other corrections (station and reflection points).
- **6** = CRUST 1.0 is used to calculate reflection-point corrections only, not for station corrections.

### **CRUST 1.0:0**

One can indicate to the program that all the stations are within an epicentral distance of less than about 50 km and that a **LOCAL OR REGIONAL MODEL** is given by setting the parameter **VERY LOCAL GEOMETRY** to '1'. Then, the ray-tracing algorithm is adjusted for a denser ray coverage to calculate the travel times for the different local/regional phases and no ellipticity corrections for the travel times are applied.

### **VERY LOCAL GEOMETRY: 0**

## 3.2.3 Group Velocities

**HYPOSAT** can use observations from different types of surface waves, for which the mean group velocities in [km/s] can be set by the following parameters:

**RG GROUP-VELOCITY: 2.5** 

**LG GROUP-VELOCITY: 3.5** 

LQ GROUP-VELOCITY: 4.4

**LR GROUP-VELOCITY: 3.95** 

Infrasound onsets and T-phases can also be included. Onset times of these phases are not well defined but mean group velocities can be used to identify such onsets.

The mean infrasound group velocity (celerity) and the T-phase mean group velocity can be set in [km/s] by:

**IS-PHASE GROUP-VEL: 0.33** 

**T-PHASE GROUP-VEL: 1.45** 

### 3.2.4 Model Uncertainties

**HYPOSAT** can account for model uncertainties by defining mean uncertainties of travel-time tables. The default value is taking no model uncertainties ('0').

**INCLUDING MODEL UNCERTAINTY: 0** 

As one implemented option, the uncertainties can be given separately for P- and S-type onsets in [s] but are assumed to be distance independent and then equal for all phases of the same phase type (P or S). These uncertainties will be added to the onset-time uncertainties and thereby influencing the weighting of the observations and the final uncertainty of the inversion results. The default values are set to 0. s for both P- and S-type onsets.

**MEAN P-WAVE MODEL UNCERTAINTY: 0.** 

**MEAN S-WAVE MODEL UNCERTAINTY: 0.** 

Another option is to define uncertainties in [s] for some specific phases separately. For now, this is possible for the following regional phases: Pg, Pb, Pn, Sg, Sb, Sn and Lg. The default values are again set to 0. s.

**MEAN PG TRAVEL-TIME UNCERTAINTY: 0.** 

**MEAN PB TRAVEL-TIME UNCERTAINTY: 0.** 

**MEAN PN TRAVEL-TIME UNCERTAINTY: 0.** 

**MEAN SG TRAVEL-TIME UNCERTAINTY: 0.** 

**MEAN SB TRAVEL-TIME UNCERTAINTY: 0.** 

**MEAN SN TRAVEL-TIME UNCERTAINTY: 0.** 

**MEAN LG TRAVEL-TIME UNCERTAINTY: 0.** 

### 3.3 STATION RELATED PARAMETERS

The program needs one file with the geographic coordinates of the sensor locations (employed station coordinates). Three file formats are supported: PDE (NEIC, see also the file *data/stations.dat* in the program package), CSS3.0, an ISC-type listing or a comma separated listing. These file formats are automatically detected. To obtain the location results faster, it is recommended to use a file containing only your network stations. The file must be either located in the run-directory, or the directory defined by the environment variable **HYPOSAT\_DATA**, or one has to give the full file name including directory path information. The default file name is '*stations.dat*'.

The four possible format definitions (Fortran) are with examples:

```
PDE (NEIC) format:
     station id, flag, lat [degrees], lat [minutes], lat [seconds], N/S, lon [degrees], lon
     [minutes], lon [seconds], E/W, elevation [m], name
     (a5,a1,i2,i2,f4.1,a1,i3,i2,f4.1,a1,f7.1,a48)
     NOA
             610223.0N 111253.1E 717.0NORSAR Array
CSS3.0 format:
     station id, start time, end time, lat [°], lon [°], elevation [km], name
     (a5,2x,i8,1x,i8,1x,f9.4,1x,f9.4,1x,a48)
     NOA
                                       61.0397
               1976275 9999365
                                                    11.2148
                                                                  0.7170 NORSAR Array
ISC-type listing format:
      1st title line
      2<sup>nd</sup> title line
     station id, lat [°], lon [°], elevation [m]
     (a5,1x,3(1x,f10.0))
                 61.0397
     NOA
                              11.2148
                                              0.7170
Comma separated ISC-type listing:
     station id, station id, lat [°], lon [°], elevation [m]
     NOA, NOA, 61.0397, 11.2148, 0.7170
          STATION FILE: ./stations.dat
```

In the case that one has two different station-coordinate lists, one can define an alternative station file, which the program will check for station coordinates if it cannot find the station in the file defined by the parameter **STATION FILE**. With this option one can also combine the usage of station lists if they have two different file formats. The default file name is also 'stations.dat'.

### **ALTERNATIVE STATION FILE: ./stations.dat**

There are several possibilities to correct onset times for station specific effects. For details on how the estimation of such corrections is implemented in **HYPOSAT** see Schweitzer (2025). This parameter is a flag if station corrections (elevation, crust) will be applied. By default, station corrections are taken in account '1'.

### **STATION CORRECTIONS: 1**

One can set global crustal velocities in [km/s] for estimating elevation corrections with these parameters. If the parameter **S-VELOCITY TO CORRECT ELEVATION** is not set or set to 0. and the parameter **P-VELOCITY TO CORRECT ELEVATION** is defined earlier in the file, the **S-VELOCITY TO CORRECT ELEVATION** is calculated by the **P-VELOCITY TO CORRECT ELEVATION** value divided by sqrt(3.). All values below 0.001 and above 99. km/s are ignored and then, the AK135 values are used as default.

*E.g.*, for AK135:

P-VELOCITY TO CORRECT ELEVATION: 99.1

**S-VELOCITY TO CORRECT ELEVATION: 99.1** 

or

P-VELOCITY TO CORRECT ELEVATION: 5.80

**S-VELOCITY TO CORRECT ELEVATION: 3.46** 

*E.g.*, for Jeffreys-Bullen:

P-VELOCITY TO CORRECT ELEVATION: 5.56

**S-VELOCITY TO CORRECT ELEVATION: 3.37** 

Station specific onset time corrections can be added in an extra file. If local seismic velocities at the stations are known, one can list them in this file and then, these values will be used to calculate station-elevation effects. Also fixed station corrections can be additionally used to correct for constant time shifts and are listed in this file.

These corrections are separate for P and S waves. For more details on station-correction calculations see Schweitzer (2025). The velocity value can also be used to correct for a known velocity anomaly below a station. The input is format free. If a station is not on this list, the default velocity values as defined by the input parameters **P-VELOCITY TO CORRECT ELEVATION** are used. In the case that one wants to use only static time corrections (*e.g.*, because of a known digitizer problem) but no special velocity values for elevation corrections, one can set the velocities to **0.** and only add the static time corrections.

```
------ example for an ASCII file containing station corrections -------
* This is a file containing values to calculate station corrections (only
* for the listed here stations!).
* All lines starting with a star '*' or empty lines are ignored.
* Minimum input:
* Station name and local P and S velocities to calculate elevation effects
* Vp or Vs given in this file for a specific station always overrides values
* given by the parameters P-VELOCITY TO CORRECT ELEVATION and
* S-VELOCITY TO CORRECT ELEVATION or defined by CRUST 1.0:
* Stat Vp Vs
GERES 5.2 3.2
* Optional input (e.g., to correct for results from tomographic studies
* or known clock errors) of static time shifts. Static corrections for P-
* and S-body waves.
* No corrections are applied to IS- or T-phase onsets. These corrections
* values will be added (!) to the observed travel times:
* Stat Vp Vs dtp dts
GERES 5.2 3.2 0. 0.
* Additional static time corrections for surface-wave type onsets (LQ, LR, Lg, Rg).
* The corrections are added (!) to the observed travel times:
* Stat Vp Vs dtp dts dtsurface
GERES 5.2 3.2 0. 0. 0.
* In the case that one wants to use only static time corrections, one can
* set the velocities to 0. (then they will be ignored) and only the static
* time corrections are used:
* Stat Vp Vs dtp dts
XYZ 0. 0. 1.0 1.0 1.0
------ end of example------
```

CAUTION: the constant time shifts, as defined in the correction file, are used to calculate travel-time residuals, but they are not changing (correcting) the observed onset times as given in *hyposat-in* or written in the output files with the **HYPOSAT** location results.

### **STATION CORRECTION FILE:**

By default, static station corrections are used for all onsets from the particular station. If the static station corrections in the **STATION CORRECTION FILE** are only valid for the 1<sup>st</sup> onsets of P or S phases (if *e.g.*, calculated with *VELEST* (see Kissling, 1988; 1995), this switch must be set to '1'.

### **STATION CORR ONLY 1ST PHASE: 0**

In the case of a very local geometry, stations may be located below the surface (e.g., in boreholes or mines) or even below the event. Then, this has to be taken in account when calculating the theoretical travel times and one must set this switch to '1'. In this case the parameter **VERY LOCAL GEOMETRY** is also set automatically to '1'. By default, this option is switched off ('0').

### **LOCAL STATION BELOW SURFACE: 0**

One can consider defining a maximum and a minimum epicentral distance of stations to be used during the inversion. Both distances are by default in [°]. But if the inversion output is set with **OUTPUT IN KM** to [km] (see below), both **MIN EPI DIST OF STAT** and **MAX EPI DIST OF STAT** are also in [km].

MIN EPI DIST OF STAT: 0.

MAX EPI DIST OF STAT: 180.

### 3.4 SOURCE RELATED PARAMETERS

The program has different ways to apply or calculate a preliminary epicenter and a preliminary source time. This can be steered with different parameters. In any case, any initial value directly given in the parameter list, will overwrite all estimated values. The following parameters define the initial solution including its uncertainties:

### 3.4.1 Initial Source Time

To set an initial source time the accepted formats are:

Epochal time (which means number of seconds since 01/01/1970

00:00:00.0) allowed is any number larger than -2840140800.0 (= default source = 1 January 1880 00:00:00.0). Any smaller number will be automatically set to

-2840140801.0.

yyyy-doy?hh?mi?ss.sss with doy (day of the year), and for '?' one can use any

character including a blank space ''. The seconds can be

omitted.

yyyy-mm-dd?hh?mi?ss.sss The seconds can be omitted.

Any time earlier than the default value will be ignored. Here some examples for the same time in the different allowed formats:

STARTING SOURCE TIME: 1970-001:00.00.00.0

**STARTING SOURCE TIME: 1970-001 00 00 00.0** 

STARTING SOURCE TIME: 1970-01-01 00:00:00.0

**STARTING SOURCE TIME: 1970-01-01 00 00 00.0** 

**STARTING SOURCE TIME: 0.** 

Together with an initial source time one can set the source time uncertainty in [s].

**STARTING TIME UNCERTAINTY: 10.** 

If no **STARTING SOURCE TIME** is set, an initial source time will be estimated from the traveltime differences between direct S-type and direct P-type observations  $(t_S - t_P)$  by using Wadati's approach (Wadati, 1932; 1933). For this, the program calculates mean Vp/Vs ratios for each observed phase type and estimates a source time, respectively. The phase types (type 1: P & S, type 2: Pg & Sg, type 3: Pn & Sn and type 4: Pb & Sb) are identified based on the global model AK135. Then, the initial source time is calculated as the mean value of all estimated source times.

In the case of only one  $t_S - t_P$  observation, the Vp/Vs ratio is set to  $\sqrt{3}$ .

If no  $t_S - t_P$  observation is available, the starting source time is set to the earliest observed onset time.

The Wadati approach can be steered by the length of the allowed  $t_{S-type} - t_{P-type}$  travel-time differences measured in [s]. By default, the minimum allowed travel-time difference is set to 0 and the maximum to 300 s.

MIN DT FOR WADATI: 0.

**MAX DT FOR WADATI: 300.** 

# 3.4.2 Initial Epicenter Estimation

If BAZ observations are available from several stations, these data are used to calculate an epicenter by calculating the possible crossing points of these different observations. A start epicenter including its uncertainties is then calculated as the mean value of all crossing points and their spread.

In the case of a single array with BAZ observations and P- and S-onset observations, the program uses these data to estimate a single array location (see *e.g.*, Schweitzer *et al.*, 2012) based on epicentral distance from the travel-time difference between the phases.

If no BAZ observations but P-type onset observations from several stations are available, the program tries a plane-wave fit through the 1<sup>st</sup> P-wave onsets at all stations to get a BAZ direction to the epicenter. Then, if possible, S-P travel-time differences are used to estimate an epicentral distance and a start epicenter is calculated. By default, this option is switched on '1'.

**PLANE WAVE APPROX: 1** 

The geographic coordinates of an initial epicenter can also be directly set together with their uncertainties. This setting will overwrite (but not when the parameter **AUTOMATIC PROCESSING** is set) evaluations based on crossing BAZ observations, the results of a **PLANE WAVE APPROX** setting, or a single array solution.

### Latitude

The allowed range is from -90 to +90 degrees, all other values as well as a '\_' are ignored and then no starting source latitude is set.

**STARTING SOURCE LATITUDE: 999.** 

or

STARTING SOURCE LATITUDE : \_

and

**STARTING LATITUDE UNCERTAINTY: 10.** 

### Longitude

The allowed range is from -180 to +180 degrees, all other values as well as a '\_' are ignored and then no starting source longitude is set.

**STARTING SOURCE LONGITUDE: 999.** 

or

STARTING SOURCE LONGITUDE: \_

and

**STARTING LONGITUDE UNCERTAINTY: 10.** 

The following parameter brings the program in an automatic processing mode. In this case, the program accepts all self- determined initial solutions and does not use in a first step the initial solutions set with the parameters above described. However, if the program cannot determine any initial solution, the set ones are used as backup. This mode can be universally set, or for teleseismic or regional events only. If this switch is set, all onsets in an ISF formatted output files will be marked with an 'a' as automatically measured. By default, automatic processing is switched off, '0'.

**AUTOMATIC PROCESSING: 0** 

**AUTOMATIC PROCESSING TELE: 0** 

**AUTOMATIC PROCESSING REGIONAL: 0** 

In the case of an ISF formatted input file, the input file already contains source location and source time. This epicenter can be used as start (and reference) solution. By default, the flag is switched off, '0'.

**ISF EPICENTER: 0** 

## 3.4.3 Initial Source Depth

One can set an initial source depth in [km] and its uncertainty, respectively. The default depth in the program is 0 km with an uncertainty of 20 km

**STARTING SOURCE DEPTH: 0.** 

**STARTING DEPTH UNCERTAINTY: 20.** 

In the case of an ISF formatted input file the depth solution can be used as start (and reference) solution. By default, this flag is switched off, '0'.

**ISF DEPTH: 0** 

An allowed depth range in [km] can be set. Be aware that the program does not allow any sources with negative depth, which may happen *e.g.*, in models with topography above the mean sea level.

**MINIMUM DEPTH: 0.** 

**MAXIMUM DEPTH: 800.** 

The depth of the event can stay fixed, or the program can try to determine the depth based on the observed data and the location of the epicenter. From **HYPOSAT 6.1** onwards, the program can also use the International Seismological Centre (ISC) default-depth definitions (see Bondár & Storchak, 2011). This can be steered with the parameter **DEPTH FLAG**, which takes the following values

- f (or F) = depth is fixed at STARTING SOURCE DEPTH.
- **d** (or **D**) = a new depth is **d**etermined from the beginning for each iteration step.
- **b** (or **B**) = **b**oth, the inversion starts with the fixed depth and when an epicenter is found, the inversion continues with inverting also for the depth.

- i (or I) = the ISC default depth (Bondár & Storchak, 2011) for this epicenter is used as fixed depth.
- **j** (or **J**) = as **b** (or **B**), but the starting depth is the ISC default depth.

By default, this parameter is set to 'F'.

### **DEPTH FLAG: F**

An additional steering parameter is needed for choosing the default depth if the parameter **DEPTH FLAG** is set to i, I, j or J. Wherever no default ISC-depth information is available, the focal depth can be fixed relative to the Moho depth as defined in CRUST 1.0. There are 3 different default depth-data sets available, which can be differently combined:

- i) default depth from ISC well-located seismicity, in a geographical grid with  $0.5^{\circ}$  x  $0.5^{\circ}$  resolution
- ii) default depth derived from the crustal thickness (Moho depth in CRUST 1.0)
- iii) default depth as defined by ISC for the different Flinn-Engdahl Regions

Only options (ii) and (iii) cover the entire globe. Therefore, one has to define how to choose the default depth type with another parameter:

```
1 = search in (i) and if not successful, continue with ii)
```

**2** = search in (i) and if not successful, continue with (iii)

**3** = search only in (ii)

**4** = search only in (iii)

By default, this parameter is set to '1'.

### **DEFAULT DEPTH TYPE: 1**

The following parameter defines how the default depth is extracted from CRUST 1.0 (see **DEFAULT DEPTH TYPE**). Here we use only the solid part of the crust (removing any water layer on top) without topography for calculating the depth and afterwards (if existing) adding the thickness of the water layer again, to avoid a source in the water layer.

```
uc = upper crust; 0.25 * CRUST 1.0 Moho depth
mc = middle crust; 0.50 * CRUST 1.0 Moho depth
lc = lower crust; 0.75 * CRUST 1.0 Moho depth
mo = Moho depth; CRUST 1.0 Moho depth
```

By default, this parameter is set to 'mc'.

### **CRUST 1.0 DEPTH TYPE: mc**

Based on model CRUST 1.0, one can force the program to not accept any source depth in a water layer at the surface (e.g., ocean, big lake). Then, the following flag has to be set to '1' (default value is '0', i.e., no check for a water layer on the top of the model).

**CHECK DEPTH FOR WATER LAYER: 0** 

### 3.5 STEERING THE USAGE OF OBSERVATIONS

### 3.5.1 Onset Time Observations and Phase Names

By default, **HYPOSAT** uses travel-time differences between different onsets at the same station as additional constraint. Setting this flag to '0' will overwrite the flag setting 'D' or 'd' for all observations in the input file *hyposat-in* and switch off the usage of travel-time differences during the inversion.

### FLAG USING TRAVEL-TIME DIFFERENCES: 1

As widely known, the reading uncertainties of seismic onset times do not follow a Gaussian distribution. **HYPOSAT** can use two different standard deviations (STD) for the onset time to weight travel-time data residuals, depending on the sign of the residual (always observation calculation). The 1<sup>st</sup> STD will then be used for positive (onset too late with respect to the theoretical value) and the 2<sup>nd</sup> STD for negative residuals (onset too early with respect to the theoretical value). For more details see Schweitzer (2006). By default, this option is switched off, '0'.

- **o** = no 2<sup>nd</sup> STD, the program uses only the STD (the *hyposat-in* description)
- 1 = reading of 2<sup>nd</sup> STD from input file (see the *hyposat-in* description)
- 2 = use the **DBLE SID. UNCERTAINTY FACTOR**

### **DOUBLE SIDED TIME UNCERTAINTY: 0**

If the flag **DOUBLE SIDED TIME UNCERTAINTY** is set to '2', the 2<sup>nd</sup> STD is defined as (STD \* **DBLE SID. UNCERTAINTY FACTOR**). The default value of this factor is '1.'.

### **DBLE SID. UNCERTAINTY FACTOR: 1.**

One can down-weight whole groups of observations. This can be steered by a 4-digit code:

1<sup>st</sup> digit: travel-time data
 2<sup>nd</sup> digit: BAZ observations
 3<sup>rd</sup> digit: slowness observations

4<sup>th</sup> digit: travel-time-difference observations

The digits can have the following values:

- no change of input uncertainties (the weighting only depends on the given uncertainties).
- = the data uncertainty for the inversion is (dynamically) increased by the residual of this observation (observation is getting a lower weight).
- **2** = the data uncertainty is reduced by a factor of 0.5 (observation is getting a higher weight).
- **3** = the data uncertainty is increased by a factor of 2 (observation is getting a lower weight).

*E.g.*, 0203 would give all BAZ observation higher weight and reduce the weight of all travel-time-difference observations. The default value is '0000' for all digits, which means no down weighting.

### **DOWNWEIGHTING TASD: 0000**

If an event location should be only based on P-type onsets one sets this here. By default, this is switched off, '0'.

### P-TYPE ONSETS ONLY: 0

One can suppress the usage of Lg or Rg phases as defining observations by setting the following parameters to '0'. By default, they are switched on '1' (if present, Lg and Rg are used).

### **REGIONAL SURFACE WAVES LG: 1**

### **REGIONAL SURFACE WAVES RG: 1**

The usage of the phase names Sg and Lg is not always consistent. Following the IASPEI recommendations for seismic phase names (Storchak *et al.*, 2002; 2003; 2006; 2009; 2011; Bormann *et al.*, 2013; Schweitzer *et al.*, 2021a), **HYPOSAT** assumes Lg to be a surface wave with a given group velocity (see **LG GROUP-VELOCITY**).

The following parameter settings can be used to homogenize the input by automatically changing the phase names for all Sg or Lg observations.

By default, both options are switched off, '0'. If both flags are set to '1', they will be both ignored.

**LG-PHASE TO SG: 0** 

**SG-PHASE TO LG: 0** 

If one wants to use both the travel times of Sg-type onsets as body-waves and the Lg onsets as surface waves, it can make sense to separate these two phases by the epicentral distance. If the following distance in [km] has a value above zero, this epicentral distance is used as separation between Sg and Lg. Then, all Lg are renamed to Sg if the epicentral distance is shorter and all Sg are renamed to Lg if the epicentral distance is equal or larger than this distance.

**SG--LG DISTANCE**: -999.

If the onset times of long-period surface waves should be used as defining observations, one must set this switch to '1'.

LP SURFACE WAVES (LQ/LR): 0

### 3.5.2 Surface Reflections in the Case of a Water Layer on Top of the Model

In the case of a **WATER LAYER ON TOP** of the model, **HYPOSAT** can correct the travel times (see also parameter settings for CRUST 1.0 and Schweitzer (2025)) for the water layer and eventually add a 'w' to the phase name. The water-layer phase is only added for P-type phases and not for any type of converted phases (*e.g.*, sP or pS). All S-type reflections and S-to-P or P-to-S converted phases are assumed to be reflected from the solid-fluid interface. The steering parameter can have these values (by default the parameter is set to '0'):

- the water layer is ignored. This is also the default case. However, the program may correct for the local velocity structure (e.g., topography) as defined with settings for the parameter CRUST 1.0.
- = all (!) reflections at the Earth's surface are corrected for the water layer, *i.e.*, not only the depth phase pP becomes pwP (Hong & Fujita, 1981; Pearce, 1981; Engdahl & Billington, 1986; Schweitzer, 2025), but also *e.g.*, PP becomes PwP. S-type onsets are then reflected at the solid-fluid interface.
- **2** = **HYPOSAT** chooses the phase identification (reflection from the solid-water interface or from the water-atmosphere interface), which minimizes the travel-time residual for P-type reflections; for S onsets as (1).
- **3** = for S-onsets as (1), optimizing for P onsets only if the travel-time difference between the two reflections (solid-water or water-atmosphere interface) is larger than **WATER LAYER DT** seconds. Otherwise, all reflections are assumed to be from the solid-water interface.
- = as (3), but if the travel-time difference is smaller than **WATER LAYER DT** seconds, all reflections are assumed to be from the water-atmosphere interface.

= the program uses the phase name(s) of the input file without any optimization. However, the program will automatically ignore all 'w' onset paths without a water layer at the reflection point in CRUST 1.0.

**WATER LAYER ON TOP: 0** 

Minimum travel-time difference in [s] to optimize the phase identification in the case of a water layer on top of the model (for details see parameter **WATER LAYER ON TOP**). The default value is 2 s, which approximately corresponds with a water depth of about 1.5 km (see Engdahl *et al.*, 1998).

**WATER LAYER DT: 2.** 

### 3.5.3 Other Non-traditional Phase Onsets

If infrasound observations (phase name IS) shall be used as defining, this switch must be set to '1'.

**IS-PHASE USAGE: 0** 

If T-phase observations (phase name T) shall be used as defining, this switch must be set to '1'.

**T-PHASE USAGE: 0** 

### 3.5.4 Backazimuth (BAZ) Observations

The backazimuth (BAZ; azimuth from station to epicenter measured from North clockwise over East) is an event location relevant datum. To make this clearer, we consequently use the term BAZ from **HYPOSAT 6.1** on. If available, BAZ information is by default used as defining observation. This can be switched off by setting this parameter to '0'.

**BAZ AS DEFINING: 1** 

If one wants to use the BAZ observations only for the estimation of an initial solution (from crossing BAZ observations) and not for the further inversion process, one can set the following parameter to '1'. This option is by default switched off, '0'.

**BAZ ONLY INIT SOL: 0** 

If one has many BAZ observations and wants to get a location based only on these observations (e.g., several infrasound array observations) one can set this flag. Then, **HYPOSAT** calculates a mean epicenter solution and its standard deviations from all possible crossing points of the BAZ observations. No travel-time information is used. This option is by default switched off, '0'.

**BAZ ONLY LOC: 0** 

The next parameter defines the maximum allowed travel-time residual in [s] of a body waves and short-period, regional surface waves (Lg, Rg) onset, for which the BAZ is used as defining observation. This setting is ignored if **USE ALL BAZ INFORMATION** is set to '1'. The default value is 30. s.

MAX T RES FOR BAZ OF B USE: 30.

The next parameter defines the maximum allowed travel-time residual in [s] of a long-period surface-wave onset, for which the BAZ is used as defining observation. This setting is ignored if **USE ALL BAZ INFORMATION** is set to '1'. The default value is 180. s.

MAX T RES FOR BAZ OF L USE: 180.

If setting the following switch to '1', the observed BAZ of all phases (also the not identified but associated ones as listed in *hyposat-in*) will be used as defining during the inversion. This option overwrites MAX T RES FOR BAZ OF B USE and MAX T RES FOR BAZ OF L USE. However, setting the option BAZ ONLY INIT SOL to '1' overwrites this flag. By default, this is switched off, '0'.

**USE ALL BAZ INFORMATION: 0** 

### 3.5.5 Slowness Observations

The slowness or ray parameter of an observed onset is either defined by its inverse, the apparent velocity in [km/s] or as spherical slowness or ray parameter in [s/°]. The program handles both, but in one input file (see *hyposat-in*), only one unit type can be used. By default, and if the input file is in ISF format, the unit is set to [s/°]. If the apparent velocity is provided in *hyposat-in* this parameter must be set to '0'.

**SLOWNESS [S/DEG]: 1** 

If the slowness observations should not be used as defining, the next switch has to be set to '0'. By default, the program uses the slowness observations '1'.

### **SLOWNESS AS DEFINING: 1**

The following parameter defines the maximum allowed travel-time residual for which the slowness is used as defining observation for body waves. The default value is set to 10 s.

**MAX T RES FOR SLOWNESS USE: 10.** 

### 3.5.6 Other Settings for Input Data

If a seismic phase name of an onset has a large residual with respect to the theoretical onset time and another seismic phase has a smaller residual, the program may try a new solution after (internally) changing the phase name. The program can also automatically declare observations as undefining (see also the parameter settings for, MAX T RES FOR BAZ OF B USE, MAX T RES FOR BAZ OF L USE, MAX T RES FOR SLOWNESS USE). However, this behavior is not always wished by the user. If the following flag is set, all observations are used for the inversion according to the setting of TASDR (see detailed description in *hyposat-in*). In this case, phase names remain unchanged and used as provided in *hyposat-in*, serving as defining observations regardless of the size of the travel-time residuals. BAZ and slowness or ray parameter observations are used as defining, as long as they have residuals less than 50° and 10 [s/°], respectively.

If this flag is set, **CONSTRAIN SOLUTION** is automatically switched off, '0'.

By default, this option is switched off, '0'. However, in the case of less than 4 observed phases, this flag is automatically set to '1'. This parameter setting is not overwriting the search for the best fitting phase name in the case of using P1 or S1 as input phase names.

### **FLAG USING INPUT FIXED: 0**

The program can check the input for more than one onset of the same phase at a given station and reduce these onsets to one entry. This option is of particular interest, whenever onset readings from several sources are merged to one single input file. The reduction (after removing double entries) is done by calculating mean onset parameters and adding the spread of the different onset parameters (time, BAZ and slowness) to the reading uncertainty of this observation.

Any amplitude/period readings will not be changed. By default, this option is switched off, '0'.

### FLAG CHECKING MULTIPLE ONSETS: 0

If **FLAG CHECKING MULTIPLE ONSETS** is set the maximum time difference between two observations to be merged into one new observation in [s] has also to be defined.

**MAX DT FOR MULTIPLE ONSETS: 5.** 

# 3.6 The Inversion Process Steering Parameters

The maximum number of iterations is arbitrarily set by default to 80 iterations.

**MAXIMUM # OF ITERATIONS: 80** 

The iterations stop when two consecutive solutions are separated by less than the given accuracy in [km].

### **LOCATION ACCURACY: 1.**

In some cases, the iteration results oscillate between two or more solutions. The following parameter defines how many iterations back we search for such oscillations. The maximum number allowed is 15; the default value is 4. In the case of an oscillating solution, the program output will internally try to jump out of this loop by changing uncertainties, data used as defining or fixing the depth. If this does not result in a stable solution, the program will list the parameter range of solutions.

### **ITERATIONS TO SEARCH OSCILLATIONS: 4**

In the case that beside onset times also BAZ and slowness or ray parameter observations are used to invert for the source location, the mean residual of all defining travel times can become unequal 0. With this parameter, the program is forced to adjust the source time for this mean shift. By default, this option is switched on '1'.

### **MEAN T-T RES. CORREC: 1**

The last iteration can constrain the solution by concentrating on the most trustable/important data and removing the other from the inversion process by declaring them as undefined (see data input in *hyposat-in*). Five different cases are implemented. If **FLAG USING INPUT FIXED** is set to '1', this parameter setting is ignored. By default, this option is switched off ('0').

- **0** = no final constraining
- 1 = final constraining of the solution by removing data with large residuals
- = final constraining by removing unimportant data as defined by the Information Density Matrix (see the Generalized Matrix Inversion (GMI) theory *e.g.*, in the textbooks of Aki & Richards (1980) or Menke (1989))

3 = case 1 & 2

4 = case 1 with fixed max residual (default 30 s)

**5** = case 4 & 2

### **CONSTRAIN SOLUTION: 0**

An additional parameter is needed for the cases 2, 3, 5 of **CONSTRAIN SOLUTION**, to define the threshold for low importance input data. All data with Information Density Matrix diagonal-element entries smaller than this threshold are then not used in the inversion. The threshold is calculated as the ratio between the actual Information Density Matrix entry for this datum and the datum with the maximum Information-Density-Matrix value. The default value is 0.005 = 0.5% of the most important datum.

However, if this value is set to any negative value, the program calculates the threshold to (1 / number of defining data).

### **INF. DENSITY MATRIX THRESHOLD: 0.005**

For the cases 4 and 5 of **CONSTRAIN SOLUTION** additional parameters are also needed. Then maximum residuals for travel-time, BAZ and slowness or ray parameter must be defined. The default values for travel-time residuals are 30 s, BAZ 50° and ray parameter 10 s/°.

**MAXIMUM ALLOWED P RESIDUAL: 30.** 

**MAXIMUM ALLOWED S RESIDUAL: 30.** 

**MAXIMUM BAZ RESIDUAL: 50.** 

**MAXIMUM SLOWNESS RESIDUAL: 10.** 

The confidence level of modelled uncertainties is measured in [%] probability. The default value is 68.3 % (*i.e.*, +/- 1 standard deviation).

**CONFIDENCE LEVEL: 68.3** 

## 3.7 MAGNITUDE CALCULATION PARAMETERS

If the data input file contains amplitude/period readings, station and network magnitudes can be estimated. By default, this option is switched off, '0'.

#### **MAGNITUDE CALCULATION: 0**

Three body wave attenuation models are available to calculate mb from 1<sup>st</sup> P-type onsets. The maximum allowed mb value is 8.5. The default model is set to 'G-R':

**G-R** = Gutenberg-Richter (1956a; 1956b), file *MB\_G-R.DAT* 

V-C = Veith-Clawson (1972), file MB\_V-C.DAT
M-R = Rezapour (2003), file MB M-R.DAT

**P-ATTENUATION MODEL: G-R** 

One can choose between two surface wave attenuation models to calculate MS from LR observations with a signal period larger than 5 s. The maximum allowed MS value is 9.5. The program uses by default 'IASPEI'.

**IASPEI** = Prague Formula from 1966 (see Willmore (1979) and citations therein)

**R-P** = formula 18 in Rezapour-Pearce (1998)

**MS-ATTENUATION MODEL: IASPEI** 

For the calculation of local/regional ML from (regional/local) S- and Lg-type onsets one can choose between three models. The maximum allowed ML value is 7.5 and the default model is 'Bath':

Note: 'Richter' ML assumes original Wood-Anderson instrument or Wood-Anderson simulated amplitude measurements in [mm] and the period information is not used.

Model file name (to be used for ML-CORRECTION FILE)

Bath = *MLCORR.TABLE* 

This period-depending attenuation relation (Båth et al., 1976) is originally only defined for periods between 0.3 and 1.4 s. The program accepts period measurement values between 0.24 s (= 4.16 Hz) and 1.68 s (= 0.595 Hz).

Richter = MLCORR.TABLE.wa

The original Wood-Anderson attenuation curve for California (Richter, 1935).

Richter = MLCORR.TABLE.wa.nicolas

A Wood-Anderson type curve for Europe modified by Nicolas et al. (1982).

**ML-ATTENUATION MODEL: Bath** 

Setting the file name (see above) defines the attenuation **ML-ATTENUATION MODEL**. The file must be either located in the run-directory, or the directory defined by the environment variable **HYPOSAT\_DATA**, or one has to give the full file name including directory path information. By default, this is set to 'MLCORR.TABLE'.

**ML-CORRECTION FILE: MLCORR.TABLE** 

All magnitude values calculated from the observations are used to calculate (mean) network magnitudes. These magnitudes are then listed in *hyposat-out* including their uncertainties.

If of interest, one can limit the distance range in [°] of contributing observations by setting one or more of the following parameters. By default, no distance limits (beside limits of the correction tables) are used.

MIN DISTANCE FOR MS: 0.

**MAX DISTANCE FOR MS: 180.** 

MIN DISTANCE FOR MB: 0.

**MAX DISTANCE FOR MB: 180.** 

MIN DISTANCE FOR ML: 0.

**MAX DISTANCE FOR ML: 20.** 

By default, only one magnitude per station and magnitude type (*i.e.*, the largest one) is used to calculate a network magnitude. If setting the following parameter all observed station magnitudes are used to calculate the network magnitude (*i.e.*, amplitude and period measurements *e.g.*, from both P and pP or sP onsets as long they are within a time window of 8 s after the 1<sup>st</sup> onset).

**All STATION MAGNITUDES: 0** 

## 3.8 I/O RELATED PARAMETERS

## 3.8.1 Input

The default data-input file name is *hyposat-in*. Here a different file name for the data-input file can be given. The default is also used when the parameter is set to ' ' or ' '.

**INPUT FILE NAME: hyposat-in** 

The *hyposat-in* format has slightly changed from **HYPOSAT 6** on. If the input file still follows the old syntax, one has to set this flag. The default is '0' for using the new syntax.

**HYPOSAT-IN OLD SYNTAX: 0** 

The final **HYPOSAT** solution can be compared with a reference hypocenter location and source time, which can be set with the following parameters. The default is that no reference location is used, '0'.

**REFERENCE EVENT: 0** 

**REFERENCE SOURCE LONGITUDE: -999.** 

**REFERENCE SOURCE LATITUDE: -999.** 

**REFERENCE SOURCE DEPTH: -999.** 

## 3.8.2 Specific Parameters for ISF 1.0-formatted Input Files

Besides data input in **HYPOSAT** format, **HYPOSAT** can also read ISF (IMS) Bulletin formatted files as data input. The input-file name can be either *hyposat-in* or any other name as set with **INPUT FILE NAME**.

By default, the input is in **HYPOSAT** format as described in Chapter 2.

**INPUT FORMAT ISF: 0** 

In the case of an ISF-formatted input file, the information about defining data (**TAS**) may be the result of an earlier location output. To force the program to use **all data** from the input file, one can set the following switch. The default setting is '0', which means using the **TAS** settings as defined by the input file.

**ISF ALL PHASES: 0** 

ISF 1.0-formatted input has no given uncertainties (standard deviations) for the observations. Therefore, these values must be set by the program. To define standard deviations of the observed data the reported quality of the onset readings is interpreted (see 'detection character' in the ISF/IMS documentation).

For higher precision onset time readings (input in milliseconds), the onset-time uncertainties set here are reduced by 20%. For non-P-type onset times, the values given here are doubled.

Standard deviation for i = impulsive onset readings (default 0.1 s):

ISF\_i: 0.1

Standard deviation for e = emergent onset readings (default 0.5 s):

ISF\_e: 0.5

Standard deviation for other, non-quality defined or q = questionable onset time readings (default 1 s):

ISF\_o: 1.

Standard deviation for BAZ observations (default 20°):

ISF\_baz: 20.

Standard deviation for slowness or ray parameter observations default (1 s/°):

ISF\_slo: 1.

In ISF-formatted files, the listed origins are identified with an author (source). Different authors are allowed but usually one location is identified as primary location. Here the author of the preferred reference location can be set. This location will then be used as reference location and as starting solution for the inversion process if **ISF EPICENTER** or **ISF DEPTH** are set.

If one wants to use the primary location, independently from the author, one has to give 'PRIME'. If the parameter is set to '\_', just the 1<sup>st</sup> origin line in the input file is used. Here some examples:

**ISF REFERENCE LOCATION: NAO** 

**ISF REFERENCE LOCATION: PRIME** 

**ISF REFERENCE LOCATION: ISC** 

ISF REFERENCE LOCATION:

## **3.8.3 Output**

One can set the author (e.g., the analyst, the network name, the project name, etc.) of the event-location inversion: a free character string with maximum 10 characters. The parameter is set by default to 'HYPOSAT'.

**AUTHOR OF SOLUTION: HYPOSAT** 

Program output is written by default in the file *hyposat-out*, which is also used when input is '\_' or ' '. This name can be changed.

**OUTPUT FILE NAME: hyposat-out** 

With this flag any output to a file can be switched off. By default, this flag is set to '1' and the output is written in the file defined by **OUTPUT FILE NAME**.

**OUTPUT SWITCH: 1** 

**HYPOSAT** can additionally write out the last location results in an ISF-formatted file. The file name is either *hyposat-out.isf* or any other name defined by the parameter **OUTPUT FILE NAME** with the automatically added extension *.isf*. The option is set by the parameter **OUTPUT FORMAT ISF**, which is set by default to ('0'), no ISF-formatted output is written.

**OUTPUT FORMAT ISF: 0** 

Any file name of the ISF formatted output file can be set with:

**ISF OUTPUT FILE: file name** 

**HYPOSAT** can additionally write the location results in a JSON file. The file name is either **hyposat-out.json** or any other name defined by the parameter **OUTPUT FILE NAME** with the automatically added extension **.json**. The option is set by the parameter **OUTPUT FORMAT JSON**, which is set by default to ('0'), no JSON-formatted output is written.

**OUTPUT FORMAT JSON: 0** 

Any file name of the JSON formatted output file can be set with:

JSON OUTPUT FILE: file name

The epicentral distance of the observations can be calculated in [km] or [°]. See also **MAX EPI DIST OF STAT** and **MIN EPI DIST OF STAT**.

If setting the flag **OUTPUT IN KM**, no ISF-formatted file can be written (**OUTPUT FORMAT ISF** is then automatically set to '0').

The default value '0' is for an epicentral-distance output in [°].

**OUTPUT IN KM:0** 

By default, all observations from stations laying outside the defined distance range (see MIN EPI DIST OF STAT and MAX EPI DIST OF STAT) are not listed in the HYPOSAT output files hyposat-out or hyposat-out.isf. If setting this flag to '1', the program lists all associated data (see the file hyposat-in) independently from the epicentral distance of the observing station.

However, these data are then still not used to calculate the solution or any event location statistics (e.g., mean residuals, azimuthal gaps, etc.).

#### **OUTPUT ALL DISTANCES: 0**

**HYPOSAT** can calculate theoretical BAZ and slowness values for all observations and write these values in the *hyposat-out* file. If theoretical values are added to the output file, no residuals are calculated, and these fields stay empty. By default, no theoretical BAZ or slowness values are listed ('0'). This parameter setting is ignored in ISF formatted output files.

- **0** = no output of theoretical values
- **1** = theoretical BAZ are given in output
- **2** = theoretical slowness values are given in output
- **3** = both (BAZ & slowness values) are given in output

#### **OUTPUT OF THEO. BAZ+P: 0**

**HYPOSAT** can also calculate for all identified body-wave onsets the corresponding emergence angles at the seismic source. This flag is by default switched off.

#### **FLAG EMERGENCE ANGLE OUTPUT: 0**

If the ISF 1.0-formatted input file contains reported quality of the onset readings (see 'detection character' in the ISF/IMS documentation) such information will be also written out by default in *hyposat-out* and *hyposat-out.isf*. Based on the settings for ISF\_i, ISF\_e and ISF\_o the applied data uncertainty during the last iteration can be translated into an uppercase 'detection character' and listed in the output files instead of the input from the ISF 1.0-formatted *hyposat-in*. The later also applies to non ISF 1.0-formatted *hyposat-in* input. Then, this flag must be set to '1'.

#### **TT DATA UNCERTAINTY OUT: 0**

**HYPOSAT** calculates two types of RMS values: one is the traditional RMS of all residuals from defining travel-time observations and the other value is the RMS calculated from the weighted residuals as done at the ISC. Both values are listed in the *hyposat-out* file. In the case of an additional ISF-formatted output file (see **OUTPUT FORMAT ISF**), the origin line contains only one place to write an RMS value. By default, the traditional RMS value is used. If the following switch is set to '1', the ISC-type RMS value is written in the ISF-formatted output file.

#### **ISC-TYPE ISF RMS: 0**

**HYPOSAT** can calculate an epicentral uncertainty ellipse based on the chosen **CONFIDENCE LEVEL** and the estimated hypocenter or epicenter and source time uncertainties. By default, this option is switched on '1'.

#### **EPICENTER UNCERTAINTY ELLIPSE: 1**

The primary and secondary azimuthal gaps (see e.g., Bondár, 2011) and the CPQ parameter (Gallacher et al., 2025) can be calculated for

- 0 = defining observations (default)
- **1** = all stations with reported observations

In any case, observations are considered only from stations in the allowed distance range (see MAX EPI DIST OF STAT and MIN EPI DIST OF STAT)

#### **AZIMUTHAL GAP FOR OBSERVATIONS: 0**

The applied local/regional model around the source can be listed at the end of the output file **hyposat-out** by setting this parameter to '1'. The default setting is no model output.

#### **OUTPUT OF REGIONAL MODEL: 0**

In ISF-formatted files, Event and Origin Identifications (IDs) can be defined.

Event ID: Any integer is allowed between 0 and 999999999. By default, it will be set to 0 (but then the number from an eventually used ISF-formatted input file is used).

## **ISF EVENT ID: 0**

An ISF-formatted file can contain several event locations for the same event. The different locations can be separated by Origin IDs. The Origin ID can be any 8- character long string.

By default ('\_') **HYPOSAT** uses, if it exists, the ID from the ISF-formatted input file.

**ISF ORIGIN ID:** 

Based on the location results and after eventually renaming and/or merging onsets, the program can write a new file in input format. The file name will be *hyposat-in.rev* or the name defined by **OUTPUT FILE NAME** with the extension *\_rev*. By default, this option is switched off '0'.

#### **FLAG NEW INPUT FILE: 0**

**HYPOSAT** has different verbosity levels for output on the screen during program execution. This level can be defined here.

If **OUTPUT LEVEL** > 10, the output level for the screen is internally calculated and an extra output file *hyposat\_gmi.out* is written with additional information about the Generalized Matrix Inversion (GMI) results. Then, the Resolution, Covariance, Correlation, and the Information- Density Matrix will be written out. A definition of the matrices can be found in *e.g.*, the textbooks of Aki & Richards (1980) or Menke (1989). The file *hyposat\_gmi.out* always contains the named matrices for the last inversion. **OUTPUT LEVEL** can be set to the following values:

OUTPUT LEVEL	Output in <i>hyposat_gmi.out</i>	Output Level on Screen
0 – 10	None	0 - 10
11	Resolution Matrix	4
12	Covariance Matrix	4
13	Correlation Matrix	4
14	All Three Matrices	4
15	п	5
16	п	6
17	п	7
18	п	8
19	п	9
20	", plus diagonal elements of the	
	Information-Density Matrix	4
21 – 29	п	as for levels 11 – 19
30	", plus whole Information-Density	
	Matrix	4
31 – 39	п	as for levels 11 – 19

As default value, the output (verbosity) level '4' is used.

#### **OUTPUT LEVEL: 4**

## 3.9 LIST OF OBSOLETE PARAMETERS AND THEIR NEW NAMES

## Old Command New Command

ATTENUATION MODEL	now	P-ATTENUATION MODEL
AZIMUTH AS DEFINING	now	BAZ AS DEFINING
AZIMUTH ONLY INIT SOL	now	BAZ ONLY INIT SOL
AZIMUTH ONLY	now	BAZ ONLY
CRUST 1.0 PATH	now	ignored
CRUST 5.1	please see for	CRUST 1.0
DBLE SID. ERROR FACTOR	now	DBLE SID. UNCERTAINTY FACTOR
DOUBLE SIDED TIME ERROR	now	DOUBLE SIDED TIME UNCERTAINTY
EPICENTER ERROR ELLIPSE	now	EPICENTER UNCERTAINTY ELLIPSE
IS PHASE GROUP-VEL	now	IS-PHASE GROUP-VEL
MAX T RES FOR AZI OF B USE	now	MAX T RES FOR BAZ OF B USE
MAX T RES FOR AZI OF L USE	now	MAX T RES FOR BAZ OF L USE
MAXIMUM ALLOWED P RESIDUUM	now	MAXIMUM ALLOWED P RESIDUAL
MAXIMUM ALLOWED S RESIDUUM	now	MAXIMUM ALLOWED S RESIDUAL
MAXIMUM AZIMUTH ERROR	now	MAXIMUM BAZ RESIDUAL
MAXIMUM BAZ RESIDUUM	now	MAXIMUM BAZ RESIDUAL
MAXIMUM SLOWNESS ERROR	now	MAXIMUM SLOWNESS RESIDUAL
MAXIMUM SLOWNESS RESIDUUM	now	MAXIMUM SLOWNESS RESIDUAL
S-ATTENUATION MODEL	see now for	MS-ATTENUATION MODEL
STARTING DEPTH ERROR	now	STARTING DEPTH UNCERTAINTY
STARTING LATITUDE ERROR	now	STARTING LATITUDE UNCERTAINTY
STARTING LONGITUDE ERROR	now	STARTING LONGITUDE UNCERTAINTY
STARTING TIME ERROR	now	STARTING TIME UNCERTAINTY
T PHASE GROUP-VEL	now	T-PHASE GROUP-VEL
USE ALL AZIMUTH INFORMATION	now	<b>USE ALL BAZ INFORMATION</b>
# TO SEARCH OSCILLATIONS	now	ITERATIONS TO SEARCH OSCILLATIONS

## 4 THE hyposat-out FILE

When executing ../bin/hyposat with the input files hyposat-parameter.tele and hyposat-in.tele located in the directory ./example/ one will get the following hyposat-out file: This example is the inversion result after running the inversion on a LINUX Centos7 system, on other systems the results might be slightly different due to numerical effects. Explanations are included in brackets []:

```
------ example for a hyposat-out file ------
NORTHERN MOLUCCA SEA, 1996 29 June, converted from pIDC's Reviewed Event Bulletin (REB)
Parameters of initial solution (+/- 1 standard deviation):
Not all possible backazimuth-observation pairs are used; if one station is more than 170 deg apart from the crossing point, this crossing point is
skipped.]

Mean epicenter calculated from 136 backazimuth observation pairs
Mean epicenter lat: 35.210 +/- 42.049 [deg]

Mean epicenter lon: 118.957 +/- 6.721 [deg]
[ type 1: S - P or S1 - P1 observation, type 2: Sg - Pg observation, type 3: Sn - Pn observation, type 4: Sb - Pb observation ]
S-P Travel-time difference type 1 with 2 observation(s)
to= 836008582.7 +/- 11.6 [s] Vp/Vs= 1.76 +/- 0.04
Mean source time: 836008582.700 +/- 11.636 [s]
Mean vp/vs: 1.758 +/- 0.035
Iterations : 9
Number of defining: 45
Reference model : ak135_A
Confidence level of given uncertainties: 68.27 \%
Source time : 1996 06 29 00 36 42.439 +/-
            or 836008602.439 +/-
or 1996-181:00.36.42.439 +/-
Epicenter lat:
Epicenter lon:
Source depth :
                                                   1.4102 +/- 0.0164 [deg]
126.3106 +/- 0.0345 [deg]
0.00 [km] Fixed by input
Epicenter uncertainty ellipse:
Major half axis: 4.19 [km] Minor half axis: 2
Azimuth: 142.1 [deg] Area: 32.78 [km^2]
Flinn-Engdahl Region ( 266 ): Northern Molucca Sea
[ Here network magnitudes for MS and mb could be calculated including their standard deviations based on the single station magnitude observation and the chosen attenuation model(s) (see magnitude parameter settings in \textit{hyposat-parameter}). ] Magnitude: 3.6 +/- 0.3 ( 2 obs, MS, R-P) Magnitude: 4.4 +/- 0.3 ( 14 obs, mb, G-R)
[ Stat - station name; Delta - epicentral distance in [deg] or [km]; Azi - azimuth from epicenter in [deg]; Phase - phase name from hyposat-in; [used] - program chosen phase name (if not identical with Phase); Onset time - hours, minutes & seconds from hyposat in; Res - travel time residual in [s]; Baz - backazimuth (from station to epicenter) in [deg]; Res - Baz residual in [deg]; Rayp - ray parameter of onset in [s/deg]; ray parameter residual in [s]; Used - usage of input data as defining; SNR - signal-to-noise ratio; Amplitude - signal amplitude in [nm]; Period - signal period in [s]. MAG - magnitude and magnitude type; Q - onset quality as defined by parameter settings in hyposat-parameter; Em-Ang - emergence angle of seismic onset
at the source in [deg]
Stat Delta Azi Ph
                                  eg] ]
Phase [used] Onset time Res Baz
                                                                                                                   Res Rayp Res Used
                                                                                                                                                                     SNR Amplitude Period MAG Q Em-Ang ARID
                                                                22.635 160.04 P
22.635 160.04 S
25.422 149.87 P1
                                                                                                                                                                                       4.50 0.300 4.44 mb E 33.63 abcdef01
                                                                                                                                                                     8.10
35.50
                                                                                                                                                                                                                     36.94 abcdef02
E 28.27 abcdef03
           25.422 149.87 P1
25.422 149.87 PcP
25.997 163.95 PcP
25.997 163.95 PcP
25.997 163.95 S
27.434 179.35 PcP
28.857 194.38 P
31.745 303.97 P
31.745 303.97 LR
                                                                                                                                                                      35.50 E 28.27 abcdef03
35.10 3.40 0.500 4.23 mb E 28.19 abcdef04
11.50 2.20 0.500 E 6.88 abcdef06
6.10 3.90 0.800 E 27.91 abcdef08
8.20 6.50 0.700 4.51 mb E 27.91 abcdef08
6.80 E 27.62 abcdef10
                                                                                         U.196 T D
-0.381 346.30 3.84 7.10 -1.96 TA D
-0.691 345.10 2.64 2.30 0.00 TASD
-3.898 347.60 5.14 20.30 4.49 A
1.012 339.40 -19.88 8.20 -0.78 T SD
0.213 T D
ASAR
 WARB
                                                                                                                                                                      6.80 E 27.62 abcderiu

4.30 0.60 0.400 3.88 mb E 27.31 abcdefil

188.80 19.360 3.87 MS E 27.27 abcdefil

27.27 abcdefil

27.27 abcdefil

27.05 abcdefil
MEEK
CMAR
CMAR
 FORT
            32.054 177.16 P
                                                                                         0.249
-0.301 7.90 -0.72 9.90 1.14 TA
            32.603 187.39 P
33.484 9.55 P
1.70 0.700 4.00 mb _ 27.05 abcdef15
                                                                                                                                                                                                                               ____ 20.42 abcdef22
____ 20.42 abcdef22
___ 18.23 abcdef23
                                                                                                                                                                                             Defining travel-time differences:
  Stat Delta Phases
                                                 Observed Res
```

```
25.422 PCP - P
25.997 PCP - P
27.434 PCP - P
36.139 PCP - P
 STKA
 Number of usable stations: 28
 [ The azimuth range of the maximum gap without any observations is always given in clockwise direction. For details about the location-accuracy measure CPQ, please see Galacher et al., 2025. ]
Maximum azimuthal gap of defining observations: 53.2 -> 136.9 [deg] = 83.7 [deg]; CPQ = 0.854
 [ The azimuth range of the maximum possible secondary gap (see Bondár et al., 2004) without any observations is always given in clockwise direction. ]
Maximum secondary azimuthal gap of defining observations: 25.4 -> 136.9 [deg] = 111.5 [deg]; CPQ = 0.769
[ The weighted RMS as used at the ISC is defined as \sqrt{\frac{\sum_{w}^{Rm^2}}{\sum_{w}^{w}}} with the above listed residuals Res and the data weights w used for the inversion (i.e., the applied standard deviations of the observed onset times) ] Weighted RMS of onset times (ISC type): 0.503 [s]
[ The weighted misfit is here defined for the L1-norm as \frac{y_{w}^{[Rei]}}{N} and for the L2-norm as \sqrt{\frac{y_{w}^{(Rei)}}{N}} with N the number of data as listed in the first colon. Input data means here also data, not used to locate the event. In this case, all backazimuth and ray parameter observations defined as usable by the switches in hyposat-in were also included. ]

Weighted misfit of input data L1 L2

33 onset times : 2.818 4.179
                                                                                                       included.
L1
2.818
1.421
1.474
1.437
                                                                                                                                        4.179
2.389
2.734
1.514
            onset times : 18 backazimuth values : 17 ray parameters : 4 travel-time differences : 72 misfit over all :
 [ The following line is a repetition of the most important inversion results TO - source time; LAT - source latitude; LON - source longitude; Z - source depth; VPVS - Vp / Vs as estimated by the Wadati approach; DLAT - latitude uncertainty; DLON - longitude uncertainty; DZ - depth uncertainty, if the depth was fixed, this is indicated here; DTO - source time uncertainty; DVPVS - VPVS uncertainty; DEF - number of defining data; RMS - root-mean-square of defining onset times]
TO LAT LON Z VPVS DLAT DLON DZ DTO DVPVS DEF RMS
 TO LAT LON Z VPVS DLAT DLON DZ DTO DVPV 1996-06-29 00 36 42.439 1.410 126.311 0.00 1.76 0.0164 0.0345 Fixed 0.089 0.04
                                                                                                                                                                                                                                                                                            DVPVS DEF
  [ However, we have still a fixed depth. Let us now try to fit the data better with another depth (see DEPTH FLAG is set to b! ]
 Iterations : 3
Number of defining: 54
Reference model : ak135_A
Confidence level of given uncertainties: 68.27 %
Source time : 1996 06 29 00 36 49.185 +/-
or 836008609.185 +/-
or 1996-181:00.36.49.185 +/-
                                                                                                                                        0.496 [s]
0.496 [s]
0.496 [s]
                                                                                          1.3221 +/- 0.0152 [deg]
126.2942 +/- 0.0360 [deg]
44.78 +/- 4.43 [km]
 Source depth :
 [ The mean travel-time residual was not zero. The source time is therefore corrected for this bias. ] Source time corrected for mean travel-time residual ( \phantom{-} -0.032 )
Source time : 1996 06 29 00 36 49.153 +/-
or 836008609.153 +/-
or 1996-181:00.36.49.153 +/-
 [ Note the now much smaller uncertainty ellipse. ]
Epicenter uncertainty ellipse:
Major half axis: 8.63 [km] Minor half axis: 1
Azimuth: 45.7 [deg] Area: 51.06 [km^2]
                                                                                                                                                                    1.88 [km]
Flinn-Engdahl Region ( 266 ): Northern Molucca Sea
Magnitude: 3.6 +/- 0.3 ( 2 obs, MS, R-P)
Magnitude: 4.4 +/- 0.3 ( 14 obs, mb, G-R)
   Stat Delta Azi Phase [used] Onset time Res
                                                                                                                                                                                     Baz
                                                                                                                                                                                                                 Res Rayp Res Used
                                                                                                                                                                                                                                                                                                     SNR
                                                                                                                                                                                                                                                                                                                           Amplitude Period MAG O Em-Ang ARID
                     22.558 159.93 P
22.558 159.93 S
25.355 149.75 P1
25.355 149.75 PcP
25.918 163.87 P
25.918 163.87 PcP
                                                                                                                    00 41 44.700 -0.978 331.50
00 45 48.700 -1.882 338.00
00 42 12.800 0.543
00 45 44.800 0.556
 WRA
                                                                                                                                                                                                               -7.11 11.10
-0.61 17.00
                                                                                                                                                                                                                                                           0.51 TASD
                                                                                                                                                                                                                                                                                                      97.80
                                                                                                                                                                                                                                                                                                                                                 4.50 0.300 4.36 mb E 50.24 abcdef01
                                                                                                                                                                                                                                                            0.65 TASD
 WRA
                                                                                                                                                                                                                                                                                                                                                                   0.900
                                                                                                                                                                                                                                                                                                      35.50
                                                                                                                                                                                                                                                                                                                                                                                                                      41.16 abcdef03
9.38 abcdef04
                                                                                                                                                               -0.457 346.30
-0.303 345.10
0.622 347.60
1.020 339.40
0.622
                                                                                                                                                                                                         3.93 7.10
2.73 2.30
5.23 20.30
-19.84 8.20
             2 25.918 163.87 PcP
2 25.918 163.87 PcP
2 25.918 163.87 PcP
3 27.347 179.32 PcP
3 27.347 179.32 PcP
3 28.768 194.39 PcP
3 31.781 304.10 PcP
3 31.781 304.10 LR
4 33.505 PcP
4 36.760 175.8 PcP
4 36.760 16.14 PcP
5 91.07 352.00 PcP
6 25.54 333.80 PcP
7 2.599 346.76 tx
81.360 200.28 PcP
8 36.740 133.86 PcP
8 36.740 1348.81 PcP
8 36.740 1348.81 PcP
8 39.733 331.71 PcP
9 99.30 332.02 PcP
1 22.997 9.01 PKPdf
1 133.094 160.82 PKPdf
1 130.604 279.88 PKPdf
1 130.604 279.88 PKPdf
1 130.604 279.88 PKPdf
1 159.429 137.09 PKPdf
                                                                                                                     00 42 16.900
00 45 45.200
                                                                                                                                                                                                                                                                                                       35.10
                                                                                                                                                                                                                                                                                                                                                 3.40
                                                                                                                                                                                                                                                                                                                                                                 0.500 4.19 mb E
                                                                                                                                                                                                                                                                                                                                                                                                                     41.02 abcdef05
9.56 abcdef06
                                                                                                                                                                                                                                                        0.00 TASD
4.49 TA D
-0.76 T SD
 ASAR
                                                                                                                                                                                                                                                                                                                                                                  0.500
                                                                                                                    00 46 45.300 0
00 42 42.700 -0
00 42 42.700 -0
00 43 9.000 -0
00 57 48.700 10
00 43 15.600 -0
00 43 15.600 -0
00 43 15.600 -0
00 43 45.700 1
01 04 25.000 25
00 43 6.800 0
00 43 6.800 0
00 43 6.800 0
00 43 6.800 0
00 43 6.800 0
00 43 6.900 -0
00 43 6.900 0
00 43 6.900 0
00 43 6.900 0
00 43 6.900 0
00 49 91.700 0
00 49 91.700 0
00 49 91.700 0
00 49 91.700 0
00 49 91.700 0
00 49 91.700 0
00 49 91.700 0
00 49 91.700 0
00 50 28.700 0
00 55 55.7100 0
00 55 56.7100 0
00 55 57.7100 0
00 55 57.7100 0
00 55 57.7100 0
  ASAR
                                                                                                                                                                                                                                                                                                         6.10
8.20
                                                                                                                                                                                                                                                                                                                                                                  0.800 E
0.700 4.41 mb E
  WARR
                                                                                                                                                               -0.169
-0.591 109.70
18.366 110.00
0.282
 MEEK
 CMAR
CMAR
                                                                                                                                                                                                                                                                                                                                           0.60 0.400 3.79 mb E
188.80 19.360 3.87 MS _
                                                                                                                                                                                                            -9.59 7.80
-9.29 39.50
                                                                                                                                                                                                                                                                                                                                                                                                            abcdef12
E 39.54 abcdef13
E 39.42 abcdef14
E 39.12 abcdef15
E 38.34 abcdef18
                                                                                                                                                                                                                                                                                                                                              4.10 0.600 4.47 mb E
                                                                                                                                                                                      7.90 -0.71 9.90
                                                                                                                                                                                                                                                          1.14 TA
                                                                                                                                                              0.349
1.012 177.30 -5.41 10.10
251.390 160.00 -22.71 46.00
0.214 323.20 -10.18 9.00
-0.160
-0.416 357.10 156.92 18.80
2.168 111.20 -52.91 6.60
                                                                                                                                                                                                                                                          1.54 TA
                                                                                                                                                                                                                                                                                                                                            1.70 0.700 4.03 mb E 38.34 abcdef18 abcdef19 7.20 0.600 4.72 mb E 12.44 abcdef19 2.00 0.550 4.17 mb E 38.09 abcdef22 2.54 abcdef28 E 25.68 abcdef22 E 25.69 abcdef22 E 25.69 abcdef22 E 25.69 abcdef22 E 25.69 abcdef22 E 20.36 abcdef23 E 20.36 abcdef24 E 20.36 abc
                                                                                                                                                                                                                                                                                                                                                1.70 0.700 4.03 mb E
  KSAR
                                                                                                                                                                                                                                                                                                        7.20
                                                                                                                                                                                                                                                                                                         8.30
                                                                                                                                                                                                                                                                                                       23.80
                                                                                                                                                                0.459
-2.733 195.90 56.30 3.90 -2.04
0.397
-0.406
                                                                                                                                                                                                                                                                                                      11 20
                                                                                                                                                               -0.406

-0.701

-3.732 94.50 15.07 4.10

-0.317 116.60 46.38 3.50

-1.017 111.20 30.81 5.90

-0.416 311.30 -118.25 1.50
                                                                                                                                                                                                                                                      -0.52
-1.11 T
1.30 T
-2.95 T
                                                                                                                                                                                                                                                                                                                                                                 0.550 4.29 mb
0.900 4.74 mb
0.550 4.19 mb
0.750 4.57 mb
  SPITS
FINES
                                                                                                                                                                                                                                                                                                                                                                                                                       19.44 abcdef30
18.77 abcdef31
7.98 abcdef33
7.97 abcdef32
  TXAR
DBIC
                                                                                                                                                               U.812 T
-0.319 311.90 106.30 6.40 4.56 T
-0.178
                                                                                                                                                                                                                                                                                                        4.40
                                                                                                                                                                                                                                                                                                                                                0.90 0.900
                                                                                                                                                                                                                                                                                                                                                                                                                           7.65 abcdef35
4.78 abcdef36
Defining travel-time differences:
```

```
Stat Delta Phases
                                                 Observed Res
WRA 22.558 S - P
QIS 25.355 PcP - P
ASAR 25.918 PcP - P
ASAR 25.918 S - P
ASAR 25.918 S - P
WASAR 25.918 S - PcP
WARB 27.347 PcP - P
STKA 36.065 PcP - P
                                                  244.000 -0.904
212.000 0.013
208.300 0.154
268.400 1.079
60.100 0.925
198.200 -0.398
145.200 -0.374
Number of usable stations: 28
[ Here we get the number of all iterations e.g., also including an earlier solution for fixed depth. ] Total number of iterations: 21
Maximum azimuthal gap of defining observations: 53.2 \rightarrow 137.1 \text{ [deg]} = 83.9 \text{ [deg]}; \text{ CPQ} = 0.853
Maximum secondary azimuthal gap of defining observations: 25.4 -> 137.1 [deg] = 111.7 [deg]; CPQ = 0.769
Residuals of defining data RMS
31 onset times : 0.654
8 backazimuth values : 5.279
8 ray parameters : 0.592
7 travel-time differences : 0.672
                                                                                          MEAN
0.000 [s]
-1.441 [deg]
-0.121 [s/deg]
0.071 [s]
                                                                    MEAN-RES
                                                                        0.552
4.416
0.525
0.550
Weighted RMS of onset times (ISC type): 0.614 [s]
Weighted misfit of input data
33 onset times :
18 backazimuth values :
17 ray parameters :
7 travel-time differences :
75 misfit over all :
TO LAT LON Z VPVS DLAT DLON DZ DTO DVPVS DEF RMS 1996-06-29 00 36 49.153 1.322 126.294 44.78 1.76 0.0152 0.0360 4.43 0.496 0.04 54 0.654
 ----- end of the hyposat-out example file -----
```

## 5 THE PROGRAM HYPOMOD AND THE hypomod-out FILE

In some cases, it may be of interest to know how well a set of observations fits with a specific source location. The program HYPOMOD calculates for a given seismic hypocenter solution the residuals for all observed data: the travel times, travel-time differences, the backazimuths and the slowness values. With the example given here for a hypocenter inversion with HYPOSAT, one has only to modify slightly the *hyposat-parameter* file and then one can execute the program HYPOMOD. The only modifications needed in *hyposat-parameter* are to set as starting source parameters the inversion results. Then, ignoring all inversion related settings in *hyposat-parameter* one will get an output-file called by default *hypomod-out*. This default name can be modified by setting the parameter OUTPUT FILE NAME in *hyposat-parameter* different than the default *hyposat-out*. The file *hypomod-out* has in principle the same format as *hyposat-out*.

**HYPOMOD** calculates residuals and the statistical parameters for this solution from **all(!)** input data as defined in the by default called *hypomod-in* input file, which has the same contents and format as *hyposat-in*. Therefore, the statistical parameters as *e.g.*, mean residuals or RMS values are different from the ones calculated after the final inversion in **HYPOSAT** (please compare with the 2<sup>nd</sup> solution in the file *hyposat-out.tele*.

No output can be written in ISF or JSON format.

----- example for changes in the *hyposat-parameter* file -----

The following *hyposat-parameter* flag is used only with **HYPOMOD**. It allows to search for the best fitting phase name for an associated body wave independently from its name given in the input file. By default, this option is switched off ('0').

#### **FLAG FREE PHASE SEARCH**: 0

Then, one has also to give the source parameters. Here the location results from the teleseismic event example in the directory ./examples/ are used (see also Chapter 4), so the file hypomod-in identical with the file hyposat-in of Chapter 2 and which was used for the example in Chapter 4. In this example the parameter FLAG FREE PHASE SEARCH was set to '1'.

**INPUT FILE NAME**: hypomod-in

**OUTPUT FILE NAME:** hypomod-out

**STARTING SOURCE LATITUDE**: 1.3221

**STARTING SOURCE LONGITUDE**: 126.2942

**STARTING SOURCE DEPTH:** 44.78

**STARTING SOURCE TIME**: 836008609.155

or

**STARTING SOURCE TIME**: 1996-181:00.36.49.155

or

**STARTING SOURCE TIME**: 1996-06-29 00:36:49.155

When running **HYPOMOD** it can also be of interest to ask for the theoretical BAZs and ray parameters (see Chapter 3 for details) from all observations (as also done in our example):

#### **OUTPUT OF THEO. BAZ+P: 3**

------ end of example ------

When executing on the Linux system the C-shell script ./run\_hypomod\_example in the directory ./examples/, you should get an output file hypomod-out looking like this with explanations included again in brackets []:

------ example for a *hypomod-out* file ------

```
HYPOMOD Version 2.2
```

Event solution by input from HYPOSAT6.2

NORTHERN MOLUCCA SEA, 1996 29 June, converted from pIDC's Reviewed Event Bulletin (REB)

Reference model : ak135\_A

The source parameters:

Source time : 1996 06 29 00 36 49.153 or 836008609.153 [s] or 1996-181:00.36.49.153

Epicenter lat: 1.3221 [deg]
Epicenter lon: 126.2942 [deg]
Source depth: 44.78 [km]

Flinn-Engdahl Region ( 266 ): Northern Molucca Sea

Magnitude: 3.6 +/- 0.3 ( 2 obs, MS, R-P) Magnitude: 4.4 +/- 0.3 ( 14 obs, mb, G-R)

Stat	Delta	Azi	Phase	[used]	0	nset	time	Res	Baz	Res	Rayp	Res	Used	SNR	Amplitude	Period	MAG	Q	Em-Ang	ARID
IRA	22.558	159.93	P		00	41	44.700	-0.978	331.50	-7.11	11.10	0.51	TASD	97.80		0.300	4.36 r	dn		
IRA	22.558	159.93	S		0.0	45	48.700	-1.882	338.00	-0.61	17.00	0.65	TASD	8.10	2.00	0.900		_	41.39	abcdef
For the	following p	hase no B	AZ or ray p	arameter obs	ervat	ions v	vere repo	rted. Becau	se of the se	etting for O	UTPUT O	F THEO. B	AZ+P to	'3', the program	fills in the theore	etical value	s without	calcu	ulating any	residuals.
IS	25.355	149.75	P1	P	0.0	42	12.800	0.544	327.49	-	9.07		T D	35.50					41.16	abcdef
IS	25.355	149.75	PcP		00	45	44.800	0.556	327.49		2.25		T D					_	9.38	abcdef
SAR	25.918	163.87	P	P	0.0	42	16.900	-0.456	346.30	3.93	7.10	-1.95	TASD	35.10		0.500	4.19 r	nb _	41.02	abcdef
SAR	25.918	163.87	PcP		0.0	45	45.200	-0.303	345.10	2.73	2.30	0.00	TASD	11.50		0.500		_	9.56	abcdef
SAR	25.918	163.87	S		00	46	45.300	0.623	347.60	5.23	20.30	4.49		6.10		0.800				abcdef
ARB	27.347	179.32	P		0.0		31.200			-19.84		-0.76		8.20		0.700			40.54	
ARB	27.347	179.32	PcP		0.0		49.400				2.40		T D					_	10.00	abcdef
EEK	28.768	194.39	P		0.0			-0.169			8.88		T	6.80				_	40.11	abcdef
MAR	31.781	304.10	P		0.0		9.000			-9.59				4.30	0.60	0.400	3.79 n	nb _	39.58	abcdef
MAR	31.781	304.10	LR		0.0			18.367		-9.29	39.50	0.45			188.80	19.360	3.87 N	1S _		abcdef
ORT	31.968	177.13	P		0.0		11.300		356.67		8.78		T	10.80				_		abcdef
OOL	32.514	187.38	P		0.0			-0.244		-0.71	9.90	1.14		8.80		0.600	4.47 n	nb _		
HK	33.5/3	9.55	P		00		25.400				8.70		T					_	39.12	abcdef
SAR	35.973						46.700			-5.41		1.54		7.20	1.70	0.700	4.03 m	nb _	38.34	abcdef
SAR	35.973							251.389				6.96			40.10	19.860	3.24 N	1S _		abcdef
TKA	36.065						46.800			-10.18		0.45		8.30	7.20	0.600	4.72 m	nb _	38.31	
TKA	36.065							-0.160			2.98		T D					_		abcdef
IJAR	36.740							-0.416								0.550				
PDY	59.107						47.000			-52.91		-0.32		23.80	4.30	0.450	4.79 r	nb_		
AL	62.534						9.000				6.67		T					_		abcdef
BKT	72.066						9.500				5.98		T					_		abcdef
RI	72.599			P	0.0	48	8.700	-2.733	195.90	56.30	3.90	-2.04	A	11.20	3.00	0.750	4.37 r	nb _	25.49	abcdef
IAW	81.360				0.0	49	1.100	0.398	64.74		5.29		T		3.00 0.80 3.60 0.60 1.10			_	22.54	abcdef
	84.471				0.0	49	17.200	-0.406	93.49		5.05		T					_	21.46	abcdef
IPO	87.451				0.0	49	31.000	-0.701	267.69		4.81		T					_	20.36	abcdef
	92.543				0.0	49	51.700	-3.732	94.50	15.07	4.10	-0.52	TAS	10.50	0.80	0.550	4.29 r	nb_	19.52	abcdef
	92.741				0.0	49	55.900	-0.317	116.60	46.38	3.50	-1.11	TAS	10.40	3.60	0.900	4.74 r	nb _	19.50	abcdef
	93.733				0.0	50	0.000	-1.017	111.20	30.81	5.90	1.30	TAS	6.60	0.60	0.550	4.19 m	nb _	19.44	abcdef
IFS	99.930															0.750	4.57 r	nb _	18.77	abcdef
										ets as PkiKP				l-time residual ]						
	122.997			PKiKP				0.310			1.97		T					_		abcdef
	123.395			PKiKP			42.700				1.98		T							abcdef
	130.604			PKiKP				-0.054			2.01		T					_		abcdef
	137.904							-0.319		106.30		4.56		4.40	0.90	0.900		_		abcdef
PAZ	159.429	137.09	PKPdf		00	56	44.700	-0.178	225.14		1.15		T					_	4.78	abcdef
efini	ng trave	el-time	differe	ences:																

## **6 REFERENCES**

- Aki, K. & Richards, P.G. (1980). Quantitative Seismology. Freeman and Company, San Francisco.
- Bolt, B. (1970). Earthquake location for small networks using the generalized inverse matrix, Bull. Seism. Soc. Amer., **60**, 1823-1828, doi: 10.1785/BSSA0600061823.
- Bondár, I. (2011). Identification and collection of ground truth events. 8 pp., doi: 10.2312/GFZ.NMSOP-2\_IS\_8.6, in NMSOP-2.
- Bondár, I. & Storchak, D.A. (2011). Improved location procedures at the International Seismological Centre. Geophys. J. Int., **186**, 1220-1244, doi: 10.1111/j.1365-246X.2011.05107.x.
- Bondár, I., Myers, S.C., Engdahl, E.R. & Bergman, E.A. (2004). Epicenter accuracy based on seismic network criteria. Geophys. J. Int., **156**, 483–496; doi10.1111/j.1365-246X.2004.02070.x.
- Bormann, P., Storchak, D.A. & Schweitzer, J. (2013). The IASPEI standard nomenclature of seismic phases. 20 pp., doi: 10.2312/GFZ.NMSOP-2\_IS\_2.1, in NMSOP-2.
- Buland, R. & Chapman, C.H. (1983), The computation of seismic travel times, Bull. Seismol. Soc. Am., **73**, 1271-1302, doi: 10.1785/BSSA0730051271.
- Båth, M., Kulhánek, O., Van Eck, T. & Wahlström, R. (1976). Engineering analysis of ground motion in Sweden. Seismological Institute, University of Uppsala, Report No. **5-76**, 48 pp. + 11 Fig.
- Dziewonski, A.M. & Anderson, D.L. (1981). Preliminary reference Earth model. Phys. Earth Planet. Inter., **25**, 297-356, doi: 10.1016/0031-9201(81)90046-7.
- Engdahl, E.R. & S. Billington (1986). Focal depth determination of Central Aleutian earthquakes. Bull. Seism. Soc. Amer. **76**, 77-93, doi: 10.1785/BSSA0760010077.
- Engdahl, E.R., van der Hilst, R. & Buland, R. (1998). Global teleseismic earthquake relocation with improved travel times and procedures for depth determination. Bull. Seism. Soc. Amer., **88**, 722-743, doi: 10.1785/BSSA0880030722.
- Gallacher, R.J., Garth T., Harris J., Bondár, I., McLaughlin, K. & Storchak, D.A. (2025). Revising the Seismic Ground Truth Reference Event Identification Criteria. In review (Seismica).
- Gutenberg, B. & Richter, C.F. (1956 a). Magnitude and energy of earthquakes. Annali Geofisica, **9**, 1-15, doi: 10.4401/ag-5590.
- Gutenberg, B. & Richter, C.F. (1956 b). Earthquake magnitude, intensity, energy, and acceleration. Bull. Seism. Soc. Amer., **46**, 105-145, doi: 10.1785/BSSA0460020105.
- Havskov, J. & Bungum, H. (1987): Source parameters for earthquakes in the northern North Sea. Norsk Geologisk Tidskrift, **67**, 51-58.
- Hong, T.-L. & K. Fujita (1981). Modelling the depth phases and source processes of some central Aleutian earthquakes. Earth Planet. Sci. Lett. **53**, 333-342, doi: 10.1016/0012-821X(81)90038-8.
- Jeffreys, H. & Bullen, K.E. (1940, 1948, 1958, 1967 & 1970). Seismological tables. British Association for the Advancement of Science, Gray Milne Trust, London, 50 pp.
- Kennett, B.L.N. (2020). Radial earth models revisited, Geophys. J. Int., **222**, 2189-2204, doi: 10.1093/gji/ggaa298.
- Kennett, B.L.N. (editor) (1991). IASPEI 1991 seismological tables. Australian National University, Research School of Earth Sciences, 167 pp.
- Kennett, B.L.N. & Engdahl, E.R. (1991). Travel times for global earthquake location and phase identification. Geophys. J. Int., **105**, 429-466, doi: 10.1111/j.1365-246X.1991.tb06724.x.
- Kennett, B.L.N., Engdahl, E.R. & Buland, R. (1995). Constraints on seismic velocities in the Earth from traveltimes. Geophys. J. Int., **122**, 108-124, doi: 10.1111/j.1365-246X.1995.tb03540.x.
- Kennett, B.L.N. & O. Gudmundsson (1996). Ellipticity corrections for seismic phases. Geophys. J. Int., **127**, 40-48, doi: 10.1111/j.1365-246X.1996.tb01533.x.
- Kissling, E. (1988), Geotomography with local earthquake data, Rev. Geophys., v26, 659–698, doi: 10.1029/RG026i004p00659.
- Kissling, E. (1995), Program VELEST user's guide—short introduction, Institute of Geophysics, ETH Zürich, https://www.seg.ethz.ch/software/velest.html (accessed 15 May 2025).

- Laske, G., Masters, G., Ma, Z. & Pasyanos, M. (2013). Update on CRUST1.0 A 1-degree global model of Earth's crust. Geophys. Res. Abstracts, **15**, Abstract EGU2013-2658 & https://igppweb.ucsd.edu/~gabi/crust1.html (accessed 15 May 2025).
- Lindholm, C.D., Schweitzer, J., Wolf, E., Bungum, H., Atakan, K., Gregersen, S., Arhe, K. & Maraska, J. (2000). Third Level Seismo-geographical Regionalization of Fennoscandia, NORSAR Scientific Report, **2-2000**, 113-118, doi: 10.21348/p.2000.0008.
- Menke, W. (1989). Geophysical data analysis: discrete inverse theory. 2<sup>nd</sup> rev. edition, 12+289 pp., Academic Press, San Diego and London.
- Morelli, A. & Dziewonski, A.M. (1993). Body-wave traveltimes and a spherically symmetric P- and S-wave velocity model. Geophys. J. Int., **112**, 178-194, doi: 10.1111/j.1365-246X.1993.tb01448.x.
- Mooney, W.D., Laske, G. & Masters, T.G. (1998). CRUST 5.1: a global crustal model at 5° x 5°. J. Geophys. Res., **103**, 727-747.
- Mykkeltveit, S. & Ringdal, F. (1981). Phase identification and event location at regional distance using small-aperture array data. In: Identification of seismic sources earthquake or underground explosion (eds. Husebye, E.S. & Mykkeltveit, S.), 467-481.
- Nicolas, M., Massinon, B., Mechler, P. & Bouchon, M. (1982). Attenuation of regional phases in western Europe. Bull. Seism. Soc. Amer., **72**, 2089-2106, doi: 10.1785/BSSA07206A2089.
- Niewiadomski, J. (1989). Application of singular value decomposition method for location of seismic events in mines. Pure Appl. Geoph., **129**, 553-570, doi: 10.1007/BF00874525.
- NMSOP (2002; 2006; 2009): New manual of seismological observatory practice (2002). Edited by P. Bormann, ISBN 3-9808780-0-7;
  - Chinese edition: P. Bormann (ed.) (2006). IASPEI New Manual of Seismological Observatory Practice (NMSOP), State Seismological Bureau, Beijing, Seismological Press, 1003 pp., ISBN 7-5028-2867-2/P (3519);
  - Revised web edition 2009:
  - https://bib.telegrafenberg.de/publizieren/bibliotheksverlag/nmsop/nmsop-2002 (accessed 15 May 2025)
- NMSOP-2 (2012): New manual of seismological observatory practice (NMSOP-2), 2<sup>nd</sup> (revised) edition (2012). Potsdam: Deutsches GeoForschungsZentrum GFZ, doi: 10.2312/GFZ.NMSOP-2. Edited by P. Bormann (2012).
- Pearce, R.G. (1981). Complex P waveforms from a Gulf of Aden earthquake. Geophys. J. R. astr. Soc. **64**, 187-200, doi: 10.1111/j.1365-246X.1981.tb02665.x.
- Pirli, M. & Schweitzer, J. (2017). BARENTS16: A 1-D velocity model for the western Barents Sea. J. Seism., **22**, 69-81, doi: 10.1007/s10950-017-9692-y.
- Russell, S., Rudge, J.F., Irving, J.C.E. & Cottaar, S. (2022). A re-examination of ellipticity corrections for seismic phases. Geophys. J. Int., **231**, 2095-2101, doi: 10.1093/gji/ggac315.
- Rezapour, M. (2003). Empirical global depth-distance correction terms for mb determination based on seismic moment. Bull. Seism. Soc. Amer., **93**, 172-189, doi: 10.1785/0120020068.
- Rezapour, M. & Pearce, R.G. (1998). Bias in surface-wave magnitude Ms due to inadequate distance corrections. Bull. Seism. Soc. Amer., **88**, 43-61, doi: 10.1785/BSSA0880010043.
- Richter, C. (1935). An instrumental earthquake magnitude scale. Bull. Seism. Soc. Amer., **25**, 1-32, doi: 10.1785/BSSA0250010001.
- Schweitzer, J. (1997). HYPOSAT a new routine to locate seismic events. NORSAR Scientific Report, **1-97/98**, 94-102, doi: 10.21348/p.1997.0014.
- Schweitzer, J. (2001). HYPOSAT an enhanced routine to locate seismic events. Pure and Applied Geophysics, **158**, 277-289, doi: 10.1007/PL00001160.
- Schweitzer, J. (2002). HYPOSAT/HYPOMOD, User manual for HYPOSAT (including HYPOMOD). PD 11.1 in NMSOP (2002, 2006, 2009) & NMSOP-2 (2012), doi: 10.2312/GFZ.NMSOP\_r1\_PD\_11.1 and 10.2312/GFZ.NMSOP-2\_PD\_11.1.
- Schweitzer, J. (2006). How can the ISC location procedures be improved? Phys. Earth Planet. Inter., **158**, 19-26, doi: 10.1016/j.pepi.2006.03.017.

- Schweitzer, J. (2018). User manual for HYPOSAT 6 and HYPOMOD 2. NMSOP-3, PD 11.1, doi: 10.2312/GFZ.NMSOP-3\_PD\_11.1, 38 pp.
- Schweitzer, J. (2025). Travel-time corrections for seismic event locations. Journal of Geological Society of India (JGSI), **101**, (6), 5 pp.
- Schweitzer, J. & Kennett, B.L.N. (2007). Comparison of location procedures The Kara Sea event of 16 August 1997. Bull. Seism. Soc. Amer., **97**, 389-400, doi: 10.1785/0120040017.
- Schweitzer, J., Storchak, D.A. & Bormann, P. (2021a). Seismic phase nomenclature: the IASPEI standard. In: Gupta, H. K. (ed.) (2021): Encyclopedia of Solid Earth Geophysics (Encyclopedia of Earth Sciences Series), 2<sup>nd</sup> edition, 1447-1459, doi: 10.1007/978-3-030-58631-7 11.
- Schweitzer J., Fyen J., Mykkeltveit, S., Gibbons, S.J., Pirli, M., Kühn D. & Kværna T. (2012). Seismic Arrays, In: NMSOP-2, Chapter 9., 80 pp., doi: 10.2312/GFZ.NMSOP-2\_ch9.
- Schweitzer, J., Paulsen, B., Antonovskaya, G.N., Fedorov, A.V., Konechnaya, Y.V., Asming, V.E. & Pirli, M. (2021b). A 24-Yr long seismic bulletin for the European Arctic. Seism. Res. Lett., **92**, 2758–2767, doi: 10.1785/0220210018.
- Storchak, D.A., Bormann, P. & Schweitzer, J. (2002). Standard nomenclature of seismic phases. In: NMSOP, IS 2.1 (2002; 2006; 2009).
- Storchak, D.A., Schweitzer, J. & Bormann, P. (2003). The IASPEI standard seismic phase list. Seism. Res. Lett., **74**, 761-772, doi: 10.1785/gssrl.74.6.761.
- Storchak, D.A., Schweitzer, J. & Bormann, P. (2011). Seismic phase names: IASPEI standard. In: Gupta, H. K. (ed.) (2011): Encyclopedia of Solid Earth Geophysics (Encyclopedia of Earth Sciences Series), ISBN: 978-1-4020-8702-0, Springer, Dordrecht, xxxvii + 1539 pp., 1162-1173, doi: 10.1007/978-90-481-8702-7\_11.
- Veith, K.F. & Clawson, G.E. (1972). Magnitude from short-period P-wave data. Bull. Seism. Soc. Amer., **62**, 435-452, doi: 10.1785/BSSA0620020435.
- Wadati, K. (1932). On the velocity ratio of seismic waves of P and S, and its application to the determination of focal depth. J. Meteorological Soc. Japan., Ser. II, **10**, (9), 540-551, doi: 10.2151/jmsj1923.10.9\_540 (in Japanese).
- Wadati, K. (1933). On the travel time of earthquake waves. Part. II. Geophys. Mag. (Tokyo), **7**, 101-111.
- Willmore, P.L. (ed.) (1979, reprinted 1982). Manual of seismological observatory practice. World Data Center A for Solid Geophysics, **Report SE-20**, Boulder, Colorado, 165 pp.

# 7 INDEX

Apparent velocity 5; 31	MLCORR.TABLE.wa.nicolas36
	REG_L3.DAT3
Backazimuth (BAZ)2;	Station coordinates 17; 18
5; 27; 28; 30; 31; 32; 35; 39; 41; 42; 49	Station corrections 19; 20
	Stations.dat3; 17; 18
Environment variable	Std_crusts.dat3; 11
HYPOSAT_DATA3; 10; 11; 13; 17; 37	
HYPOSAT_PARA8	Infrasound phase (IS)15; 19; 30; 31
Generalized Matrix Inversion (GMI)	libtau-software2; 10; 11
3; 34; 44	Onsat time
i/o files	Onset time
Crust1.bnds3	2; 5; 6; 15; 18; 20; 22; 27; 29; 32; 34; 39
Crust1.vp3	P velocity (Vp)12; 19
Crust1.vs3	P velocity (vp)12, 13
elcordir.tbl3	Parameter settings
grn_def_depth.ak135.dat3	ALL STATION MAGNITUDES
hypomod-in49	ALTERNATIVE STATION FILE
hypomod-out3; 49; 50; 51	AUTHOR OF SOLUTION
hyposat gmi.out44	AUTOMATIC PROCESSING23
hyposat-in3; 5; 6; 7; 11;	AUTOMATIC PROCESSING REGIONAL . 23
12; 20; 27; 31; 32; 34; 38; 41; 42; 49	AUTOMATIC PROCESSING TELE 23
hyposat-in.rev43	AZIMUTHAL GAP FOR OBSERVATIONS
hyposat-in.tele46	43
hyposat-out	BAZ AS DEFINING
3; 5; 37; 40; 41; 42; 43; 46; 48; 49	BAZ ONLY INIT SOL30; 31
hyposat-out.isf40; 41; 42	BAZ ONLY LOC
hyposat-out.json41	CHECK DEPTH FOR WATER LAYER 26
hyposat-out.tele49	CONFIDENCE LEVEL
hyposat-parameter3; 5; 6; 8; 9; 46; 49	CONSTRAIN SOLUTION35
hyposat-parameter_all8	CRUST 1.0
isc_def_depth.dat3	CRUST 1.0 DEPTH TYPE25
ISF file	DBLE SID. UNCERTAINTY FACTOR 27
8; 12; 23; 24; 31; 38; 39; 40; 41; 42; 43	DEFAULT DEPTH TYPE25
JSON file8; 41	DEPTH FLAG24; 25
Local or regional model12; 13	DOUBLE SIDED TIME UNCERTAINTY
MB G-R.DAT3; 36	6; 27
MB_M-R.DAT3; 36	DOWNWEIGHTING TASD28
MB_V-C.DAT3; 36	EPICENTER UNCERTAINTY ELLIPSE 42
ML correction36; 37	FLAG CHECKING MULTIPLE ONSETS
MLCORR.TABLE3; 36; 37	32; 33
MLCORR.TABLE.nicolas3	FLAG EMERGENCE ANGLE OUTPUT 42
MLCORR.TABLE.wa3; 36	FLAG FREE PHASE SEARCH49; 50

FLAG NEW INPUT FILE43	MAX DT FOR WADATI22
FLAG USING INPUT FIXED32; 34	MAX EPI DIST OF STAT20; 41; 43
FLAG USING TRAVEL-TIME DIFFERENCES	MAX T RES FOR BAZ OF B USE 31; 32
27	MAX T RES FOR BAZ OF L USE31
GLOBAL CRUSTAL MODEL CODE11	MAX T RES FOR SLOWNESS USE 32
GLOBAL MODEL6; 10; 11	MAXIMUM # OF ITERATIONS34
GLOBAL MODEL 110; 11	MAXIMUM ALLOWED P RESIDUAL 35
GLOBAL MODEL 26; 11; 12	MAXIMUM ALLOWED S RESIDUAL 35
GLOBAL MODEL 36; 11	MAXIMUM BAZ RESIDUAL35
GLOBAL MODEL 46; 11	MAXIMUM DEPTH24
HYPOSAT-IN OLD SYNTAX38	MAXIMUM SLOWNESS RESIDUAL 35
INCLUDING MODEL UNCERTAINTY15	MEAN LG TRAVEL-TIME UNCERTAINTY
INF. DENSITY MATRIX THRESHOLD35	16
INPUT FILE NAME38; 49	MEAN PB TRAVEL-TIME UNCERTAINTY
INPUT FORMAT ISF38	16
ISC-TYPE ISF RMS43	MEAN PG TRAVEL-TIME UNCERTAINTY
ISF ALL PHASES39	16
ISF DEPTH24; 40	MEAN PN TRAVEL-TIME UNCERTAINTY
ISF EPICENTER24; 40	16
ISF EVENT ID43	MEAN P-WAVE MODEL UNCERTAINTY
ISF ORIGIN ID43	15
ISF OUTPUT FILE41; 42	MEAN SB TRAVEL-TIME UNCERTAINTY
ISF REFERENCE LOCATION40	16
ISF 2ND MODEL DISTANCE12	MEAN SG TRAVEL-TIME UNCERTAINTY
ISF baz39	16
ISF_e39; 42	MEAN SN TRAVEL-TIME UNCERTAINTY
ISF_i39; 42	16
ISF_039; 42	MEAN S-WAVE MODEL UNCERTAINTY
ISF_slo39	15
IS-PHASE GROUP-VEL15	MEAN T-T RES. CORREC34
IS-PHASE USAGE30	MIN DISTANCE FOR MB37
ITERATIONS TO SEARCH OSCILLATIONS	MIN DISTANCE FOR ML37
34	MIN DISTANCE FOR MS37
JSON OUTPUT FILE41	MIN DT FOR WADATI22
LG GROUP-VELOCITY15; 28	MIN EPI DIST OF STAT20; 41; 43
LG-PHASE TO SG28	MINIMUM DEPTH24
LOCAL OR REGIONAL MODEL 12; 13; 14	ML CORRECTION FILE36; 37
LOCAL STATION BELOW SURFACE20	ML-ATTENUATION MODEL36; 37
LOCATION ACCURACY34	MS-ATTENUATION MODEL36
LP SURFACE WAVES29	OUTPUT ALL DISTANCES41
LQ GROUP-VELOCITY15	OUTPUT FILE NAME 40; 41; 43; 49
LR GROUP-VELOCITY15	OUTPUT FORMAT ISF 40; 41; 43
MAGNITUDE CALCULATION36	OUTPUT FORMAT JSON41
MAX DISTANCE FOR MB37	OUTPUT IN KM 20; 41
MAX DISTANCE FOR ML37	OUTPUT LEVEL44
MAX DISTANCE FOR MS37	OUTPUT OF REGIONAL MODEL43
MAX DT FOR MULTIPLE ONSETS33	OUTPUT OF THEO. BAZ+P 42; 50

OUTPUT SWITCH40	S velocity (Vs)12; 19
P-ATTENUATION MODEL36	
PHASE INDEX FOR LOCAL MODEL14	Seismic phases
PLANE WAVE APPROX22; 23	Lg15; 16; 19; 28; 29; 36
P-TYPE ONSETS ONLY28	LQ15; 19; 29
P-VELOCITY TO CORRECT ELEVATION	LR15; 19; 29; 36
18; 19	P6; 12; 13; 15; 29; 37
REFERENCE EVENT38	P'P'P'2
REFERENCE SOURCE DEPTH38	P'wP'3
REFERENCE SOURCE LATITUDE38	P15
REFERENCE SOURCE LONGITUDE38	Pb13; 16
REGIONAL SURFACE WAVES LG28	PbP2; 13
REGIONAL SURFACE WAVES RG28	PbPb13
RG GROUP-VELOCITY15	PbPbPb13
SGLG DISTANCE29	PbS13
SG-PHASE TO LG28	PcPPcP2
SLOWNESS [S/DEG]5; 31	Pg12; 13; 16
SLOWNESS AS DEFINING32	PgPg13
STARTING DEPTH UNCERTAINTY24	PgPgPg2; 13
STARTING LATITUDE UNCERTAINTY23	PmP2; 13
STARTING LONGITUDE UNCERTAINTY	PmS13
23	Pn12; 13; 16
STARTING SOURCE DEPTH24; 49	PnPn13
STARTING SOURCE LATITUDE23; 49	PnPnPn13
STARTING SOURCE LONGITUDE23; 49	pP3; 13; 29; 37
STARTING SOURCE TIME21; 22; 50	PP3; 29
STARTING TIME UNCERTAINTY21	pP'P'2
STATION CORR ONLY 1ST PHASE20	pPb13
STATION CORRECTION FILE20	pPcP2
STATION CORRECTIONS18	pPg13
STATION FILE17; 18	pPn
S-VELOCITY TO CORRECT ELEVATION	pPP2
18; 19	PPP
T-PHASE GROUP-VEL15	pS13; 29
T-PHASE USAGE30	pSb13
TT DATA UNCERTAINTY OUT42	pSg13
USE ALL BAZ INFORMATION5; 31	pSn
VERY LOCAL GEOMETRY14	pwP3; 29
WATER LAYER DT29; 30	PwP3; 29
WATER LAYER ON TOP29; 30	Px (PX)5
	Rg15; 19
Program version 2; 3; 4; 8; 9; 10; 24; 38	rx (RX)5
HYPOMOD_HISTORY.md2	S6; 12; 13; 15; 29; 36
HYPOSAT_HISTORY.md2	S'S'S'
B	S15
Ray parameter 2; 5; 6; 31; 32; 34; 35; 39	S3KS2
	Sb13; 16

SbP13	Travel-time differences 2; 6; 22; 27
SbS2; 13	
SbSb13	Uncertainty2
SbSbSb13	Data28; 32
ScSScS2	Double sided6; 27
Sg12; 13; 16; 28; 29	Ellipse42
SgSg13	Initial23; 24
SgSgSg13	Model15; 16; 21
SmP13	Results 15
SmS2; 13	
Sn12; 13; 16	Velocity model
SnSn13	Conrad2; 12; 13
SnSnSn2; 13	Global2; 3; 6; 10; 12
SP13; 29; 37	2 <sup>nd</sup> model & ISF input12
SPb13	AK13510; 11; 22
SPg13	AK135 with regional upper mantle 10
SPn13	Crustal code11
SS13	EK137 10; 11
SSb13	IASPEI 1991 10; 11
SScS2	Jeffreys-Bullen
SSg13	PREM
SSS2; 13	Groug velocity
Sx (SX)5	Local / regional13; 14
T15; 30	CRUST 1.0
tx (TX)5	2; 3; 6; 12; 14; 19; 25; 26; 29; 30
x (X)5	Maximum distance
× (×)	Output
Slowness5; 6; 27; 31; 32; 34; 35; 39; 41;	Very local geometry14
42; 49	Model uncertainty15
42, 43	Moho2; 12; 13; 25
Station 2; 3; 5; 6; 12; 14;	Regional
17; 20; 22; 27; 30; 32; 36; 37; 41; 42; 43	BARENTS16 11
Coordinates17; 18	BAREY11
Corrections12; 14; 18; 19; 20	BAREZ11
Corrections12, 14, 10, 19, 20	BERGEN11
	FESCAN11





