

This manual documents GnuCOBOL 3.2, 31 December 2021 at 18:25 GMT. build.

Document Copyright 2009-2014 Gary L. Cutler, FSF (Free Software Foundation). Updates: Copyright 2014-2021 Vincent B. Coen, Gary L. Cutler & FSF.

The authors and copyright holders of the COBOL programming language itself used herein:

FLOW-MATIC (trademark for Sperry Rand Corporation) Programming for the Univac(R) I & II. Data Automation Systems copyrighted 1958, 1959, by Sperry Rand Corporation; IBM commercial translator form F28-8013, copyrighted 1959 by IBM; FACT DSI27A5260-2760, copyrighted 1960 by Minneapolis-Honeywell, have specifically authorised the use of this material in whole or in part of the COBOL specifications. Such authorisation extends to the reproduction & use of COBOL specifications in programming manuals or similar publications.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License [FDL], Version 1.3 or any later version published by the Free Software Foundation; with Invariant Section "Introduction", no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

Table of Contents

GnuCOBOL Programmer's Guide	1
1. Introduction	3
1.1. Additional Reference Sources	
1.2. Introducing COBOL	
1.2.1. Why YOU Should Learn COBOL	
1.2.2. Programmer Productivity	
1.3. So What is GnuCOBOL?	
2. COBOL Fundamentals	9
2.1. The COBOL Language - The Basics	9
2.1.1. Language Reserved Words	
2.1.2. User-Defined Words	10
2.1.3. Case Insensitivity	10
2.1.4. Readability of Programs	
2.1.5. Divisions Organize Programs	
2.1.6. Copybooks	13
2.1.7. Structured Data	13
2.1.8. Files	13
2.1.9. Table Handling	17
2.1.10. Sorting and Merging Data	17
2.1.11. String Manipulation	
2.1.12. Screen Formatting Features	
2.1.12.1. A Sample Screen	20
2.1.12.2. Color Palette and Video Attributes	20
2.1.13. Report Writer Features	22
2.1.14. Data Initialization	23
2.1.15. Syntax Diagram Conventions	24
2.1.16. Format of Program Source Lines	
2.1.17. Program Structure	28
2.1.18. Comments	30
2.1.19. Literals	31
2.1.19.1. Numeric Literals	31
2.1.19.2. Alphanumeric Literals	31
2.1.19.3. Figurative Constants	32
2.1.20. Punctuation	33
2.1.21. Interfacing to Other Environments	33
2.2. The COBOL Language - Advanced Techniques	
2.2.1. Table References	35
2.2.2. Qualification of Data Names	36
2.2.3. Reference Modifiers	
2.2.4. Arithmetic Expressions	
2.2.5. Conditional Expressions	41
2.2.5.1. Condition Names	41
2.2.5.2. Class Conditions	42
2.2.5.3. Sign Conditions	44

2.2.5.4. Switch-Status Conditions	45
2.2.5.5. Relation Conditions	
2.2.5.6. Combined Conditions	47
2.2.5.7. Negated Conditions	48
2.2.6. Use of Periods	49
2.2.7. Use of VERB/END-VERB Constructs	50
2.2.8. Concurrent Access to Files	
2.2.8.1. File Sharing	52
2.2.8.2. Record Locking	54
3. CDF - Compiler Directing Facility	57
3.1. >>CALL-CONVENTION	
3.2. COPY	
3.3. REPLACE	
3.4. >>DEFINE	
3.5. >>IF	
3.6. >>SET	
3.7. >>SOURCE	
3.8. >>TURN	
3.9. >>D	
3.10. >>DISPLAY	
3.11. >>PAGE	
3.12. >>LISTING	
3.13. >>LEAP-SECONDS	
3.14. \$ Directives	
3.15. Predefined compilation variables	75
4. IDENTIFICATION DIVISION	
5. ENVIRONMENT DIVISION	79
5.1. CONFIGURATION SECTION	80
5.1.1. SOURCE-COMPUTER	81
5.1.2. OBJECT-COMPUTER	
5.1.3. SPECIAL-NAMES	84
5.1.3.1. Alphabet-Name-Clause	88
5.1.3.2. Class-Definition-Clause	90
5.1.3.3. Switch-Definition-Clause	91
5.1.3.4. Symbolic-Characters-Clause	
5.1.4. REPOSITORY	93
5.2. INPUT-OUTPUT SECTION	
5.2.1. SELECT	95
5.2.1.1. ORGANIZATION SEQUENTIAL	100
5.2.1.2. ORGANIZATION LINE SEQUENTIAL	101
5.2.1.3. ORGANIZATION RELATIVE	
5.2.1.4. ORGANIZATION INDEXED	
5.2.2. SAME RECORD AREA	107
	108

Contents 31 December 2021

GnuCOBOL 3.2	[31	December	2021	at	18:25	GMT.	Programmer	.'s	\mathbf{G}	1116	16

- 1	1	1

6.	DATA DIVISION	109
	6.1. Data Definition Principles	. 110
	6.2. FILE SECTION	. 112
	6.2.1. File/Sort-Description	. 113
	6.2.2. FILE-SECTION-Data-Item	. 116
	6.3. WORKING-STORAGE SECTION	. 118
	6.4. LOCAL-STORAGE SECTION	. 120
	6.5. LINKAGE SECTION	
	6.6. REPORT SECTION	
	6.6.1. Report Group Definitions	
	6.6.2. REPORT SECTION Data Items	
	6.7. SCREEN SECTION	
	6.8. Special Data Items	
	6.8.1. 01-Level Constants	
	6.8.2. 66-Level Data Items	
	6.8.3. 77-Level Data Items	
	6.8.4. 78-Level Data Items	
	6.8.5. 88-Level Data Items	
	6.9. Data Description Clauses	
	6.9.1. ANY LENGTH	
	6.9.2. AUTO	
	6.9.3. AUTO-SKIP	
	6.9.4. AUTOTERMINATE	
	6.9.5. BACKGROUND-COLOR	
	6.9.6. BASED	
	6.9.7. BEEP	
	6.9.8. BELL	
	6.9.9. BLANK	
	6.9.10. BLANK WHEN ZERO	
	6.9.11. BLINK	
	6.9.12. COLUMN	
	6.9.13. CONSTANT	
	6.9.14. EMPTY-CHECK	
	6.9.15. ERASE	
	6.9.16. EXTERNAL	
	6.9.17. FALSE	
	6.9.18. FOREGROUND-COLOR	. 158
	6.9.19. FROM	
	6.9.20. FULL	
	6.9.21. GLOBAL	. 161
	6.9.22. GROUP INDICATE	. 162
	6.9.23. HIGHLIGHT	. 163
	6.9.24. JUSTIFIED	
	6.9.25. LEFTLINE	. 165
	6.9.26. LENGTH-CHECK	
	6.9.27. LINE	
	6.9.28. LOWLIGHT	
	6.9.29. NEXT GROUP	
	6.9.30. NO-ECHO	
	6.9.31. OCCURS	
	6.9.32. OVERLINE	
	6.9.33. PICTURE	
	6.9.34 PRESENT WHEN	182

6.9.35. PROMPT	183
6.9.36. PROTECTED	184
6.9.37. REDEFINES	185
6.9.38. RENAMES	186
6.9.39. REQUIRED	
6.9.40. REVERSE-VIDEO	
6.9.41. SECURE	
6.9.42. SIGN IS	
6.9.43. SOURCE	
6.9.44. SUM OF	
6.9.45. SYNCRONIZED	
6.9.46. TO	
6.9.47. TYPE	
6.9.48. UNDERLINE	
6.9.49. USAGE	
6.9.50. USING	
6.9.51. VALUE	207
7 DDOGEDIDE DIVIGION	011
7. PROCEDURE DIVISION	
7.1. PROCEDURE DIVISION USING	
7.2. PROCEDURE DIVISION CHAINING	
7.3. PROCEDURE DIVISION RETURNING	
7.4. PROCEDURE DIVISION Sections and Paragraphs	
7.5. DECLARATIVES	
7.6. Common Clauses on Executable Statements	
7.6.1. AT END + NOT AT END	
7.6.2. CORRESPONDING	
7.6.3. INVALID KEY + NOT INVALID KEY	
7.6.4. ON EXCEPTION + NOT ON EXCEPTION	
7.6.5. ON OVERFLOW + NOT ON OVERFLOW	
7.6.7. ROUNDED	
7.7. Special Registers	
7.8. GnuCOBOL Statements	
7.8.1. ACCEPT	
7.8.1.1. ACCEPT FROM CONSOLE	
7.8.1.2. ACCEPT FROM COMMAND-LINE	
7.8.1.3. ACCEPT FROM ENVIRONMENT	
7.8.1.4. ACCEPT data-item	
7.8.1.5. ACCEPT FROM DATE/TIME	
7.8.1.6. ACCEPT FROM Screen-Info	
7.8.1.7. ACCEPT FROM Runtime-Info	
7.8.1.8. ACCEPT OMITTED	243
7.8.1.9. ACCEPT FROM EXCEPTION-STATUS	244
7.8.2. ADD	245
7.8.2.1. ADD TO	245
7.8.2.2. ADD GIVING	247
7.8.2.3. ADD CORRESPONDING	249
7.8.3. ALLOCATE	250
7.8.4. ALTER	$\dots 252$
7.8.5. CALL	
7.8.6. CANCEL	
7.8.7. CLOSE	258

GnuCOBOL 3.2	[31 D	ecember)	2021	at	18:25	GMT.]	Programmer	.'s	G	11ic	le

_	u
١	7

7.8.8. COMMIT	259
7.8.9. COMPUTE	260
7.8.10. CONTINUE	261
7.8.11. DELETE	262
7.8.12. DISPLAY	263
7.8.12.1. DISPLAY UPON device	263
7.8.12.2. DISPLAY UPON COMMAND-LINE	264
7.8.12.3. DISPLAY UPON ENVIRONMENT-NAME	265
7.8.12.4. DISPLAY Data-Item	266
7.8.12.5. DISPLAY data-item	268
7.8.13. DIVIDE	269
7.8.13.1. DIVIDE INTO	269
7.8.13.2. DIVIDE INTO GIVING	
7.8.13.3. DIVIDE BY GIVING	273
7.8.14. ENTRY	275
7.8.15. EVALUATE	276
7.8.16. EXHIBIT	280
7.8.17. EXIT	
7.8.18. FREE	285
7.8.19. GENERATE	
7.8.20. GOBACK	
7.8.21. GO TO	
7.8.21.1. Simple GO TO	
7.8.21.2. GO TO DEPENDING ON	
7.8.22. IF	
7.8.23. INITIALIZE	
7.8.24. INITIATE	
7.8.25. INSPECT	
7.8.26. MERGE	
7.8.27. MOVE	
7.8.27.1. Simple MOVE	
7.8.27.2. MOVE CORRESPONDING	
7.8.28. MULTIPLY	
7.8.28.1. MULTIPLY BY	
7.8.28.1. MULTIPLY GIVING	
7.8.29. OPEN	
7.8.29. OPEN	
7.8.30.1. Procedural PERFORM	
7.8.30.2. Inline PERFORM	
7.8.31. READ	
7.8.31.1. Sequential READ	
7.8.31.2. Random READ	
7.8.32. READY TRACE	
7.8.33. RELEASE	
7.8.34. RESET TRACE	
7.8.35. RETURN	
7.8.36. REWRITE	
7.8.37. ROLLBACK	
7.8.38. SEARCH	
7.8.39. SEARCH ALL	
7.8.40. SET	
7 8 40 1 SET ENVIRONMENT	330

7.8.40.2. SET Program-Pointer	
7.8.40.3. SET ADDRESS	332
7.8.40.4. SET Index	333
7.8.40.5. SET UP/DOWN	
7.8.40.6. SET Condition Name	335
7.8.40.7. SET Switch	336
7.8.40.8. SET ATTRIBUTE	
7.8.40.9. SET LAST EXCEPTION	
7.8.41. SORT	
7.8.41.1. File-Based SORT	
7.8.41.2. Table SORT	
7.8.42. START	
7.8.43. STOP	
7.8.44. STRING	
7.8.45. SUBTRACT	
7.8.45.1. SUBTRACT FROM	
7.8.45.2. SUBTRACT GIVING	
7.8.45.3. SUBTRACT CORRESPONDING	
7.8.46. SUPPRESS	
7.8.47. TERMINATE	
7.8.48. TRANSFORM	
7.8.49. UNLOCK	
7.8.50. UNSTRING	
7.8.51. WRITE	
7.0.91. WIGHE	
9 Functions	262
8. Functions	
8.1. Intrinsic Functions	
8.1.1. ABS	
8.1.2. ACOS	
8.1.3. ANNUITY	
8.1.4. ASIN	
8.1.5. ATAN	
8.1.6. BYTE-LENGTH	
8.1.7. CHAR	
8.1.8. COMBINED-DATETIME	
8.1.9. CONCATENATE	
8.1.10. COS	
8.1.11. CURRENCY-SYMBOL	
8.1.12. CURRENT-DATE	
8.1.13. DATE-OF-INTEGER	
8.1.14. DATE-TO-YYYYMMDD	
8.1.15. DAY-OF-INTEGER	
8.1.16. DAY-TO-YYYYDDD	379
8.1.17. E	
8.1.18. EXCEPTION-FILE	
8.1.19. EXCEPTION-LOCATION	
* * * * * * * * * * * * * * * * * * * *	0.00
8.1.20. EXCEPTION-STATEMENT	
8.1.21. EXCEPTION-STATUS	
8.1.21. EXCEPTION-STATUS. 8.1.22. EXP. 8.1.23. EXP10. 8.1.24. FACTORIAL	

GnuCOBOL 3	2 [31 December 2021 at 18:25 GMT.] Programmer's Guide	vii
8.1.27. F	ORMATTED-DATETIME	391
8.1.28. F	FORMATTED-TIME	392
8.1.29. F	FRACTION-PART	393
8.1.30. H	HIGHEST-ALGEBRAIC	394
8.1.31. I	NTEGER	395
8.1.32. I	NTEGER-OF-DATE	396
8.1.33. I	NTEGER-OF-DAY	397
8.1.34. I	NTEGER-OF-FORMATTED-DATE	398
8.1.35. I	NTEGER-PART	399
8.1.36. I	ENGTH	400
8.1.37. I	ENGTH-AN	401
8.1.38. I	OCALE-COMPARE	402
8.1.39. I	OCALE-DATE	403
8.1.40. I	OCALE-TIME	404
8.1.41. I	OCALE-TIME-FROM-SECONDS	405
8.1.42. I	.OG	406
	OG10	
8.1.44. I	OWER-CASE	408
8.1.45. I	OWEST-ALGEBRAIC	409
8.1.46. N	MAX	410
	MEAN	
	MEDIAN	
8.1.49. N	MIDRANGE	413
8.1.50. N	/IIN	414
	MOD	
	MODULE-CALLER-ID	
	MODULE-DATE	
	MODULE-FORMATTED-DATE	
	MODULE-ID	
8.1.56. N	MODULE-PATH	420
	MODULE-SOURCE	
	MODULE-TIME	
	MONETARY-DECIMAL-POINT	
	MONETARY-THOUSANDS-SEPARATOR	
	NUMERIC-DECIMAL-POINT	
	NUMERIC-THOUSANDS-SEPARATOR	
	NUMVAL	
	NUMVAL-C	
	NUMVAL-C-V2.	
	NUMVAL-F	
	ORD	
8.1.67. (ORD-MAX	432
	ORD-MIN	
	PI	
	PRESENT-VALUE	
	RANDOM	
	RANGE	
	REM	
	REVERSE	
	SECONDS-FROM-FORMATTED-TIME	
	ECONDS-PAST-MIDNIGHT	
	IGN	
	IN	

31 December 2021 Contents

	8.1.79. SQRT	. 445
	8.1.80. STANDARD-DEVIATION	446
	8.1.81. STORED-CHAR-LENGTH	447
	8.1.82. SUBSTITUTE	448
	8.1.83. SUBSTITUTE-CASE	449
	8.1.84. SUM	
	8.1.85. TAN	451
	8.1.86. TEST-DATE-YYYYMMDD	. 452
	8.1.87. TEST-DAY-YYYYDDD.	. 453
	8.1.88. TEST-FORMATTED-DATETIME	454
	8.1.89. TEST-NUMVAL	455
	8.1.90. TEST-NUMVAL-C.	. 456
	8.1.91. TEST-NUMVAL-F	. 457
	8.1.92. TRIM	
	8.1.93. UPPER-CASE	
	8.1.94. VARIANCE	
	8.1.95. WHEN-COMPILED	461
	8.1.96. YEAR-TO-YYYY	. 462
	8.1.97. BOOLEAN-OF-INTEGER	463
	8.1.98. CHAR-NATIONAL	
	8.1.99. DISPLAY-OF	
	8.1.100. EXCEPTION-FILE-N.	
	8.1.101. EXCEPTION-LOCATION-N	. 467
	8.1.102. INTEGER-OF-BOOLEAN	. 468
	8.1.103. NATIONAL-OF.	
	8.1.104. STANDARD-COMPARE	
	8.1.105. BIT-OF.	
	8.1.106. BIT-TO-CHAR	
	8.1.107. HEX-OF	
	8.1.108. HEX-TO-CHAR	
8.2	2. Built-In System Subroutines	
	8.2.1. C\$CALLEDBY	
	8.2.2. C\$CHDIR	
	8.2.3. C\$COPY	
	8.2.4. C\$DELETE	
	8.2.5. C\$FILEINFO	
	8.2.6. C\$GETPID	
	8.2.7. C\$JUSTIFY	_
	8.2.8. C\$MAKEDIR	
	8.2.9. C\$NARG	
	8.2.10. C\$PARAMSIZE	
	8.2.11. C\$PRINTABLE	
	8.2.12. C\$SLEEP	
	8.2.13. C\$TOLOWER	
	8.2.14. C\$TOUPPER	
	8.2.15. CBL_AND	
	8.2.16. CBL_CHANGE_DIR.	
	8.2.17. CBL_CHECK_FILE_EXIST	
	8.2.18. CBL_CLOSE_FILE	
	8.2.19. CBL_COPY_FILE	
	8.2.20. CBL_CREATE_DIR	
	8.2.21. CBL_CREATE_FILE	
	8.2.22. CBL_DELETE_DIR	
	UNDER UNDER THE PROPERTY OF TH	. IJO

GnuCOBOL 3.2 [31 December 2021 at 18:25 GMT.] Programmer's Guide	ix
8.2.23. CBL_DELETE_FILE.	499
8.2.24. CBL_EQ	500
8.2.25. CBL_ERROR_PROC	
8.2.26. CBL_EXIT_PROC	503
8.2.27. CBL_FLUSH_FILE	505
8.2.28. CBL_GC_FORK	506
8.2.29. CBL_GC_GETOPT	
8.2.30. CBL_GC_HOSTED	
8.2.31. CBL_GC_NANOSLEEP	
8.2.32. CBL_GC_PRINTABLE	
8.2.33. CBL_GC_WAITPID	
8.2.34. CBL_GET_CSR_POS	
8.2.35. CBL_GET_CURRENT_DIR.	
8.2.36. CBL_GET_SCR_SIZE.	
8.2.37. CBL_IMP	
8.2.38. CBL_NIMP	
8.2.39. CBL_NOR.	
8.2.40. CBL_NOT	
8.2.42. CBL_OPEN_FILE	
8.2.43. CBL_OR	
8.2.44. CBL_READ_FILE	
8.2.45. CBL_READ_KBD_CHAR	
8.2.46. CBL_RENAME_FILE.	
8.2.47. CBL_SET_CSR_POS.	
8.2.48. CBL_TOLOWER	
8.2.49. CBL_TOUPPER	
8.2.50. CBL_WRITE_FILE.	
8.2.51. CBL_XOR	
8.2.52. SYSTEM	
8.2.53. X"91"	
8.2.54. X"E4"	
8.2.55. X"E5"	
8.2.56. X"F4"	
8.2.57. X"F5"	
0.2.07. A 10	
9. Report Writer Usage	$\dots 537$
9.1. RWCS Lexicon	$\dots 537$
9.2. The Anatomy of a Report	
9.3. The Anatomy of a Report Page	$\dots 538$
9.4. How RWCS Builds Report Pages	539
9.5. Control Hierarchy	540
9.6. An Example	$\dots 542$
9.6.1. Data	$\dots 542$
9.6.2. Program	544
9.6.3. Generated Report Pages	548
9.7. Control Hierarchy (Revisited)	
9.8. Turning PHYSICAL Page Formatting Into LOGICAL Formatting	556

31 December 2021 Contents

10. Interfacing With The OS	559
10.1. Compiling Programs	559
10.1.1. cobc - The GnuCOBOL Compiler	559
10.1.1.1. cobc option -Xref an example	568
10.1.1.2. Cross Reference listing using cobxref	569
10.1.2. Compilation Time Environment Variables	$\dots \dots 571$
10.1.3. Predefined Compilation Variables	572
10.1.4. Locating Copybooks	$\dots \dots 574$
10.1.5. Compiler Configuration Files	574
10.2. Running Programs	582
10.2.1. Direct Execution	582
10.2.2. Executing Dynamically-Loadable Libraries	582
10.2.2.1. cobcrun - Command-line Execution	582
10.2.2.2. Dynamically Loaded Subprograms	583
10.2.3. Run Time Environment Variables	
10.2.3.1. General instructions	
10.2.3.2. General Environment	587
10.2.3.3. Call Environment	589
10.2.3.4. File I/O	590
10.2.3.5. Screen I/O	
10.2.3.6. Report I/O	
10.2.3.7. File I/O Environment Variables and/or dictionary file	
10.2.4. Program Arguments	
10.3. Binary Truncation	599
11. Sub-Programming	603
11.1. Subprogram Types	
11.2. Independent vs Contained vs Nested Subprograms	
11.3. Alternate Entry Points	
11.4. Dynamic vs Static Subprograms	
11.5. Subprogram Execution Flow	
11.5.1. Subprogram Execution Flow	
11.5.2. User-Defined Function Execution Flow	
11.6. Sharing Data Between Calling and Called Programs	
11.6.1. Subprogram Arguments	
11.6.1.1. Calling Program Considerations	
11.6.1.2. Called Program Considerations	
11.6.2. GLOBAL Data Items	
11.6.3. EXTERNAL Data Items	
11.7. Recursive Subprograms	
11.8. Combining GnuCOBOL and C Programs	
11.8.1. GnuCOBOL Run-Time Library Requirements	
11.8.1. GnuCOBOL Run-Time Library Requirements	
11.8.2. String Allocation Differences between Glucobole and C	
11.8.4. GnuCOBOL Main Programs CALLing C Subprograms	
11.8.5. C Main Programs Calling GnuCOBOL Subprograms	
11.0.0. O Main I rograms Canng OnuCODOD Dubpiograms	

Contents 31 December 2021

GnuCOBOL 3.2 [31 December 2021 at 18:25 GMT.] Programmer's Guide	xi
12. Programming Style Suggestions	621
12.1. Marking Changes in Programs. 12.2. Data Item Coding and Naming Conventions 12.3. Table Subscripting versus Table Indexing 12.4. Copybook Naming Conventions and Usage 12.5. PROCEDURE DIVISION Sections Versus Paragraphs 12.6. COMPUTE Versus ADD-SUBTRACT-MULTIPLY-DIVIDE	621 622 623 625 625
Appendix A - Glossary of Terms	629
Appendix B - Reserved Word Lists	637
Appendix C1 - Grouped Word Lists by	
feature and function	639
Common reserved words	639
Extra (obsolete) context sensitive words	657
Internal registers	658
Appendix C2 - Intrinsic Functions	659
Appendix C3 - System routines	663
Appendix C4 - System names System names: device. System names: feature. System names: switch.	665
Appendix D - GNU Free Documentation License	
Appendix E - Summary of Document Changes	673
Appendix F4 - Summary of Compiler Changes for	
COBOL Compiler v4 early dev	677
Appendix F3 - Summary of Compiler Changes for v3.1.1-Dev	679
Appendix F2 - Summary of Compiler Changes after GnuCOBOL Compiler v2.2	691
Appendix F1 - Summary of Compiler Changes since 2009 and version v1-1	699
Index	709

31 December 2021 Contents

GnuCOBOL Programmer's Guide

This manual documents the 31 December 2021 at 18:25 GMT. build of GnuCOBOL 3.2.

31 December 2021 Contents

1. Introduction

This document describes the syntax, semantics and use of the COBOL programming language as implemented by GnuCOBOL, formerly known as OpenCOBOL.

The original principal developers of GnuCOBOL were Keisuke Nishida and Roger While. Since then, many members of the community have been involved in its development.

This document is intended to serve as a fully functional reference and light user's guide, suitable for both those readers learning COBOL for the first time as a light training tool, as well as those already familiar with another dialect of COBOL.

A separate manual — containing only the details of the GnuCOBOL implementation and designed for experienced COBOL programmers — has been taken from this guide. That document (GnuCOBOL Quick Reference) contains no training subject matter.

Other documents that should be read is the <code>gnucobol.pdf</code> found in the <code>doc</code> directory of the compiler sources and the file <code>NEWS</code> supplied with the source code of the <code>GnuCOBOL</code> compiler, in the top-level directory. There you will find the latest COBOL language features that have been added, some of which may not be in this document due to time constraints. If you find any, please report it as a bug for the Programmer's Guide so that it can be fixed.

Yet another document which delves deeper in to the compiler that is a *must* read, is the FAQ available via the GnuCOBOL Manuals and Guides (https://gnucobol.sourceforge.io/#faq), although it could do with a wee clean up to ease reading and finding required information.

1.1. Additional Reference Sources

For those wishing to learn COBOL for the first time, Gary can strongly recommend the following resources.

If you like to hold a book in your hands, I strongly recommend *Murach's Structured COBOL*, by Mike Murach, Anne Prince and Raul Menendez (2000) - ISBN 9781890774059. Mike Murach and his various writing partners have been writing outstanding COBOL textbooks for decades. It's an excellent book for those familiar with the concepts of programming in other languages, but unfamiliar with COBOL.

Another to consider is COBOL Unleashed by Jon Wessler, et al (with many other contributors) dated 1998 - ISBN 9780672312540 - 1,000 pages, which is perhaps more geared to the mainframe but with much related to other platform including for GnuCOBOL which Vincent finds very useful at times.

One more is Beginning COBOL for Programmers Paperback 20 Mar. 2014 by Michael Coughlan - ISBN 978-1430262534 which may well be worth a read. There are many others.

Would you prefer a web-based tutorial? Try the University of Limerick (Ireland) - COBOL web site (http://www.csis.ul.ie/cobol/).

In addition there is the GnuCOBOL FAQ (https://gnucobol.sourceforge.io/faq/index.html) — which has now exceeded 1,400 pages — available as HTML or a downloadable .pdf file.

Along with every release of the compiler sources is the file NEWS. It contains up to the minute updates regarding the compiler and additional COBOL language elements which may well *not* be yet included in this manual.

1.2. Introducing COBOL

If you already know a programming language other than COBOL, chances are that language is Java, C or C++. You will find COBOL much different from those; sometimes the differences are

a good thing and sometimes they aren't. The thing to remember about COBOL is this: it was designed to solve business problems.

COBOL, first introduced to the programming public in 1959, was the very first programming language to become standardized (in 1960). This meant that a standard-compliant COBOL program written on computer "A" made by company "B" would be able to be compiled and executed on computer "X" made by company "Y" with very few, if any, changes. This may not seem like such a big deal today, but it was a radical departure from all programming languages that came before it and even many that came after it.

The name COBOL actually says it all — COBOL is an acronym that stands for " (\mathbf{CO}) mmon (\mathbf{B}) usiness (\mathbf{O}) riented (\mathbf{L}) anguage". Note the fact that the word "common" comes before all others. The word "business" is a close second. Therein lies the key to COBOL's success.

1.2.1. Why YOU Should Learn COBOL

Despite statements from industry "insiders", the COBOL programming language is not dead, even though newer and so-called "modern" languages like Java, C#, .NET, Ruby on Rails and so on appear to have become the languages of choice in the Information Technology world. These languages have become popular because they address the following desired requirements for "modern" programming:

- 1. They conform to the principles of Object-Oriented Programming (OOP). This is desired for one major reason it facilitates "code re-usability", thus improving the productivity of programmers by allowing them to re-use previously written (and debugged) code in new applications. For one reason or another, COBOL is perceived as being weak in this regard. It isn't (especially today), as we'll see in the next section, but perception is important.
- 2. Those languages aren't limited to mainframe computers, as COBOL is *perceived* to be. Some, like .NET and Ruby, aren't even *available* on mainframes. The "modern" programming languages were designed and intended for use on the full variety of computer platforms, from shirt-pocket computers (i.e. smart phones) up to the most massive of supercomputers.
- 3. There are several excellent commercially available COBOL implementations available for non-mainframe systems (Micro Focus COBOL, AccuCOBOL, NetCOBOL and Elastic COBOL, just to name a few), including Windows and UNIX/Linux systems. These aren't cheap, however.
- 4. Universities love the "Modern" languages. In the U.S., 73% of colleges lack even one COBOL course on their curricula. COBOL, it appears, is no longer "cool" enough for students to fill a classroom.

Just because COBOL doesn't traditionally support objects, classes, and the like doesn't mean that its "procedural" approach to computing isn't valuable — after all, it runs 70% of the worlds business transactions, and does so:

- Using programs that, for the most part, are much more self-documenting than would be the case with any other programming language.
- Effortlessly providing arithmetic accuracy to 31 digits, with performance approaching that of well-written assembly-language programs. Don't think this isn't critically important to banks, investment houses and any business interested in tracking revenues, expenses and profits (duh like ALL of them).
- Integrating well with non-COBOL infrastructures such as XML, SOA, MQ, almost any DBMS, Transaction Processing platforms, Queue-Management facilities and other programming languages.

• By running on almost as many different computing platforms as Java can. You can't run COBOL programs in your smart phone, but desktops, workstations, midframes/servers, mainframes and supercomputers are all fair game.

Today's IT managers and business leaders are faced with a challenging dilemma — how do you maintain the enormous COBOL code base that is still running their businesses when academia has all but abandoned the language they need their people to use to keep the wheels rolling? The problem is compounded by the fact that those programmers that are skilled in COBOL are retiring and taking their knowledge with them. In some markets, this appears to be having an inflationary effect on the cost of resources (COBOL programmers) whose supply is becoming smaller and smaller. The pressure to update applications to make use of more up-to-date graphical user interfaces is also perceived as a reason to abandon COBOL in favour of GUI-friendly languages such as Java.

Businesses are addressing the COBOL challenge in different ways:

- 1. By undertaking so-called "modernization projects", where existing applications are either rewritten in "modern" languages or replaced outright with purchased packages. Most of these businesses are using such activities as an excuse to abandon "expensive" mainframes in favour of (presumably) less-expensive "open systems" (mid frame/server) solutions.
- 2. Many times these businesses are finding the cost of the system/networking engineering, operational management and monitoring and risk management (i.e. disaster recovery) infrastructures necessary to support truly mission-critical applications to be so high that the "less-expensive" solution really isn't; in these cases the mainframe may remain the best option, thus leaving COBOL in play and businesses seeking another solution for at least part of their application base.
- 3. Training their own COBOL programmers. Since colleges, universities and technical schools have lost interest in doing so, many businesses have undertaken the task of "growing their own" new crop of COBOL programmers. Fear of being pigeon-holed into a niche technology is a factor inhibiting many of today's programmers from willingly volunteering for such training.
- 4. By moving the user-interface onto the desktop; such efforts involve running modern-language front-end clients on user desktops (or laptops or smart phones, etc.) with COBOL programs providing server functionality on mainframe or midframe platforms, providing all the database and file "heavy lifting" on the back-end. Solutions like this provide users with the user-interfaces they want/need while still leveraging COBOL's strengths on (possibly) downsized legacy mainframe or midframe systems.

It's probably a true that an IT professional can no longer afford to allow COBOL to be the only wrench in their toolbox, but with a massive code base still in production now and for the foreseeable future, adding COBOL to a multi-lingual curriculum vitae (CV) and/or resume (yes — they ARE different) is not a bad thing at all. Knowing COBOL as well as the language du-jour will make you the smartest person in the room when the discussion of migrating the current "legacy" environment to a "modern" implementation comes around.

You'll find COBOL an easy language to learn and a FAR EASIER language to master than many of the "modern" languages.

The whole reason you're reading this is that you've discovered GnuCOBOL — another implementation of COBOL in addition to those mentioned earlier. The distinguishing characteristic of GnuCOBOL versus those others is that GnuCOBOL is FREE open-source and therefore FREE to obtain and use. It is community-enhanced and community-supported. Later in this document (see [So What is GnuCOBOL?], page 7), you'll begin to learn more about this COBOL implementation's capabilities.

1.2.2. Programmer Productivity

Throughout the history of computer programming, the search for new ways to improve of the productivity of programmers has been a major consideration. Other than hobbyists, programming is an activity performed for money, and businesses abhor spending anything more than is absolutely necessary; even government agencies try to spend as little money on projects as is absolutely necessary.

The amount of programming necessary to accomplish a given task — including rework needed by any errors found during testing (testing is sometimes jokingly defined as: that time during which an application is actually in production, allowing users to discover the problems) is the measure of programmer productivity. Anything that reduces that effort will therefore reduce the time spent in such activities therefore reducing the expense of same. When the expense of programming is reduced, programmer productivity is increased.

Sometimes the quest for improved programmer productivity (and therefore reduced programming expense) has taken the form of introducing new features in programming languages, or even new languages altogether. Sometimes it has resulted in new ways of using the existing languages.

While many technological and procedural developments have made *evolutionary* improvements to programmer productivity, each of the following three events has been responsible for *revolutionary* improvements:

- The development of so-called "higher-level" programming languages that enable a programmer to specify in a single statement of the language an action that would have required many more separate statements in a prior programming language. The standardization of such languages, making them usable on a wide variety of computers and operating systems, was a key aspect of this development. COBOL was a pioneering development in this area, being a direct descendant of the very first higher-level language (FLOW-MATIC, developed by US Naval Lieutenant Grace Hopper) and the first to become standardized.
- The establishment of programming techniques that make programs easier to read and therefore easier to understand. Not only do such techniques reduce the amount of rework necessary simply to make a program work as designed, but they also reduce the amount of time a programmer needs to study an existing program in order how to best adapt it to changing business requirements. The foremost development in this area was structured programming. Introduced in the late 1970's, this approach to programming spawned new programming languages (PASCAL, ALGOL, PL/1 and so forth) designed around it. With the ANSI 85 standard, COBOL embraced the principles espoused by structured programming mayens as well as any of the languages designed strictly around it.
- The establishment of programming techniques AND the introduction of programming language capabilities to facilitate the re-usability of program code. Anything that supports code re-usability can have a profound impact to the amount of time it takes to develop new applications or to make significant changes to existing ones. In recent years, object-oriented programming (OOP) has been the industry "poster child" for code re-usability. By enabling program logic and the data structures that logic manipulates to be encapsulated into easily stored and retrieved (and therefore "reusable") modules called classes, the object-oriented languages such as Java, C++ and C# have become the favourites of academia. Since students are being trained in these languages and only these, by and large, it's no surprise that today object-oriented programming languages are the darlings of the industry.

The reality is, however, that good programmers have been practising code re-usability for more than a half-century. Up until recently, COBOL programmers have had some of the best code re-usability tools available — they've been doing it with copybooks and subprograms rather than classes, methods and attributes but the net results have been similar. With

the COBOL2002 and the COBOL 2014 standards, the COBOL programming language has become just as "object-oriented" as the "modern" languages, while preserving the ability to support, modify, compile and execute "legacy" COBOL programs as well.

While GnuCOBOL supports few of the OOP programming constructs defined by the COBOL2002 and COBOL2014 standards, it supports every aspect of the ANSI 85 standard and therefore fully meets the needs of points #1 and #2, above. With its supported feature set (see [So What is GnuCOBOL?], page 7), it provides significant programmer productivity capabilities.

1.3. So What is GnuCOBOL?


GnuCOBOL is a free and open sourced COBOL compiler and runtime environment, written using the C programming language. GnuCOBOL is typically distributed in source-code form, and must then be built for your computer's operating system using the system's C compiler and loader. While originally developed for the UNIX and Linux operating systems, GnuCOBOL has also been successfully built for computers running OSX and Windows utilizing the UNIX-emulation features of such tools as Cygwin and MinGW. Also see the GNU website (https://savannah.gnu.org/projects/gnucobol) for more information at.

The MinGW approach is a personal favourite with the author of this manual because it creates a GnuCOBOL compiler and runtime library that require only a single MinGW DLL to be available for the GnuCOBOL compiler, runtime library and user programs. That DLL is freely distributable under the terms of the GNU General Public License. A MinGW build of GnuCOBOL fits easily on and runs from a 128MB flash drive with no need to install any software onto the Windows computer that will be using it. Some functionality of the language, dealing with the sharing of files between concurrently executing GnuCOBOL programs and record locking on certain types of files, is sacrificed however as the underlying operating system routines needed to implement them aren't available to Windows and aren't provided by MinGW. The current version for MinGW is available at the download link along with various other platforms at the GnuCOBOL download website (https://sourceforge.net/projects/open-cobol/files/gnu-cobol).

GnuCOBOL has also been built as a truly native Windows application utilizing Microsoft's freely-downloadable Visual Studio Express package to provide the C compiler and linker/loader. This approach does not lend itself well to a "portable" distribution.

The GnuCOBOL compiler generates C code from your COBOL programs; that C code is then automatically compiled and linked using your system's C compiler (typically, but not limited to, gcc).

GnuCOBOL fully supports much of the ANSI 85 standard for COBOL (the only major exclusion is the Communications Module) and also supports some of the components of the COBOL2002 and COBOL2014 standards, such as the SCREEN SECTION (see [SCREEN SECTION], page 131), table-based SORT (see [Table SORT], page 342) and user-defined functions. There are others with more being added almost weekly.



2. COBOL Fundamentals

This chapter describes the syntax, semantics and usage of the COBOL programming language as implemented by the current version of GnuCOBOL. For the rest of this document the Language is spelt as COBOL to ease reading however the compiler name retains the mixed case of GnuCOBOL.

This document is intended to serve as a full-function reference and user's guide suitable for both those readers learning COBOL for the first time as usage as a training tool, as well as those already familiar with some dialects of the COBOL language.

A separate manual exists that just contains the details of the Cobol grammar as implemented in GnuCOBOL, which is designed strictly for experienced COBOL programmers and this is taken from this guide. This does NOT contain any training subject matter.

These extra manuals are: GnuCOBOL Quick Reference containing just the COBOL semantics / grammar in a short document while the other, GnuCOBOL Sample Programs, shows detailed example Cobol programs with indication of syntax used in each program.

For each implementation of the GnuCOBOL compiler the supplied files NEWS should also be read for any last minute updates along with files README and INSTALL for building the compiler.

2.1. The COBOL Language - The Basics

2.1.1. Language Reserved Words

Cobol programs consist of a sequence of words and symbols. Words, which consist of sequences of letters (upper- and/or lower-case), digits, dashes ('-') and/or underscores ('_') may have a pre-defined, specific, meaning to the compiler or may be invented by the programmer for his/her purposes.

The GnuCOBOL language specification defines over 1130 Reserved Words — words to which the compiler assigns a special meaning. This list and number applies to the default list which covers many implementations and that it is possible to limit the list to either a specific implementation via -std=xyz[-strict] or to manually unreserve words if they are used in existing sources as user-defined words.

Programmers may use a reserved word as part of a word they are creating themselves, but may not create their own word as an exact duplicate (without regard to case) of a COBOL reserved word. Note that a reserved word includes all classes, such as intrinsic functions, mnemonics names, system routines and reserved words. The list of reserved words can be changed by adding or removing specific words for a given compile or as a default by use of the steering command -std and -conf. See the specific config files that are by default, held in /usr/local/share/gnucobol/config. Also using the option 'FUNCTION ALL INTRINSIC', will add another 100+ reserved words. These can be modified to match the requirements of a business or project team but be warned that these are updated when a new version of the compiler is built so might be more prudent to create your own configuation based on an existing one but with a different name.

In addition, you can add and/or remove reserved words by adding one of these options to cobe to add -freserved-words=value or -freserved=word or, to remove, -fnot-reserved=word. As well as -freserved=word:alias to create an alias for a word as well as -fnot-register=word or -fregister=word to remove or add, a special register word.

See Appendix C for a complete list of GnuCOBOL reserved words .

For any given version of GnuCOBOL you can also list the full current set of reserved words by running cobc with --list-reserved, --list-intrinsic, --list-system as well as --list-mnemonics. Again subject to variation depending on usage of the --std line command.

2.1.2. User-Defined Words

When you write GnuCOBOL programs, you'll need to create a variety of words to represent various aspects of the program, the program's data and the external environment in which the program will run. This will include internal names by which data files will be referenced, data item names and names of executable logic procedures.

User-defined words may be composed from the characters 'A' through 'Z' (upper- and/or lower-case), '0' through '9', dash ('-') and underscore ('_'). User-defined words may neither start nor end with hyphen or underscore characters.

Other programming languages provide the programmer with a similar capability of creating their own words (names) for parts of a program; COBOL is somewhat unusual when compared to other languages in that user-defined words may *start* with a digit.

With the exception of logic procedure names, which may consist entirely of nothing but digits, user-defined words must contain at least one letter.

2.1.3. Case Insensitivity

All COBOL implementations allow the use of both upper and lower case letters in program coding. GnuCOBOL is completely insensitive to the case used when writing reserved words or user-defined names. Thus, AAAAA, aaaaa, Aaaaa and AaAaA are all the same word as far as GnuCOBOL is concerned.

The only time the case used does matter is within quoted character strings, where character values will be exactly as coded.

By convention throughout this document, COBOL reserved words will be shown entirely in UPPER-CASE while those words that were created by a programmer will be represented by tokens in mixed or lower case.

This isn't a bad practice to use in actual programs, as it leads to programs where it is much easier to distinguish reserved words from user-defined ones!

2.1.4. Readability of Programs

Critics of COBOL frequently focus on the wordiness of the language, often citing the case of a so-called "Hello World" program as the "proof" that COBOL is so much more tedious to program in than more "modern" languages. This tedium is cited as such a significant impact to programmer productivity that, in their opinions, COBOL can't go away quickly enough.

Here are two different "Hello World" applications, one written in Java and the second in GnuCOBOL. First, the Java version:

```
Class HelloWorld {
    public static void main(String[] args) {
        System.out.println("Hello World!");
    }
}
And here is the same program, written in GnuCOBOL:
IDENTIFICATION DIVISION.
PROGRAM-ID. HelloWorld.
PROCEDURE DIVISION.
```

```
DISPLAY "Hello World!".
```

Both of the above programs could have been written on a single line, if desired, and both languages allow a programmer to use (or not use) indentation as they see fit to improve program readability. Sounds like a tie so far.

Let's look at how much more "wordy" COBOL is than Java. Count the characters in the two programs. The Java program has 95 (not counting carriage returns and any indentation). The COBOL program has 89 (again, not counting carriage returns and indentation)! Technically, it could have been only 65 because the IDENTIFICATION DIVISION. header is actually optional. Clearly, "Hello World" doesn't look any more concise in Java than it does in COBOL.

Let's look at a different problem. Surely a program that asks a user to input a positive integer, generates the sum of all positive integers from 1 to that number and then prints the result will be MUCH shorter and MUCH easier to understand when coded in Java than in COBOL, right?

```
You can be the judge. First, the Java version:
 import java.util.Scanner;
 public class sumofintegers {
     public static void main(String[] arg) {
         System.out.println("Enter a positive integer");
         Scanner scan=new Scanner(System.in);
         int n=scan.nextInt();
         int sum=0;
         for (int i=1;i<=n;i++) {
             sum+=i;
         }
         System.out.println("The sum is "+sum);
     }
 }
And now for the COBOL version:
 IDENTIFICATION DIVISION.
 PROGRAM-ID. SumOfIntegers.
 DATA DIVISION.
 WORKING-STORAGE SECTION.
 01 n
       BINARY-LONG.
 01 i
        BINARY-LONG.
 01 sum BINARY-LONG VALUE 0.
 PROCEDURE DIVISION.
 DISPLAY "Enter a positive integer"
 ACCEPT n
 PERFORM VARYING i FROM 1 BY 1 UNTIL i > n
     ADD i TO sum
 END-PERFORM
 DISPLAY "The sum is " sum.
```

My familiarity with COBOL may be prejudicing my opinion, but it doesn't appear to me that the Java code is any simpler than the COBOL code. In case you're interested in character counts, the Java code comes in at 278 (not counting indentation characters). The COBOL code is 298 (274 without the IDENTIFICATION DIVISION. header).

Despite what you've seen here, the more complex the programming logic being implemented, the more concise the Java code will appear to be, even compared to 2002-standard COBOL. That conciseness comes with a price though — program code readability. Java (or C or C++ or

C#) programs are generally intelligible only to trained programmers. COBOL programs can, however, be quite understandable by non-programmers. This is actually a side-effect of the "wordiness" of the language, where COBOL statements use natural English words to describe their actions. This inherent readability has come in handy many times throughout my career when I've had to learn obscure business (or legal) processes by reading the COBOL program code that supports them.

The "modern" languages, like Java, also have their own "boilerplate" infrastructure overhead that must be coded in order to write the logic that is necessary in the program. Take for example the public static void main(String[] arg) and import java.util.Scanner; statements. The critics tend to forget about this when they criticize COBOL for its structural "overhead".

When it first was developed, COBOL's easily-readable syntax made it profoundly different from anything that had been seen before. For the first time, it was possible to specify logic in a manner that was — at least to some extent — comprehensible even to non-programmers. Take for example, the following code written in FORTRAN — a language developed only a year before COBOL:

```
EXT = PRICE * IQTY
INVTOT = INVTOT + EXT
```

With its original limitation on the length of variable names (one- to six-character names comprised of a letter followed by up to five letters and/or digits), its implicit rule that variables were automatically created as real (floating-point) unless their name started with a letter in the range I-N, and its use of algebraic notation to express actions being taken, FORTRAN wasn't a particularly readable language, even for programmers. Compare this with the equivalent COBOL code:

```
MULTIPLY price BY quantity GIVING extended-amount ADD extended-amount TO invoice-total
```

Clearly, even a non-programmer could at least conceptually understand what was going on! Over time, languages like FORTRAN evolved more robust variable names, and COBOL introduced a more formula-based syntactical capability for arithmetic operations, but FORTRAN was never as readable as COBOL.

Because of its inherent readability, I would MUCH rather be handed an assignment to make significant changes to a COBOL program about which I know nothing than to be asked to do the same with a C, C++, C# or Java program.

Those that argue that it is too boring / wasteful / time-consuming / insulting (pick one) to have to code a COBOL program "from scratch" are clearly ignorant of the following facts:

- Many systems have program-development tools available to ease the task of coding programs; those tools that concentrate on COBOL are capable of providing templates for much of the "overhead" verbiage of any program...
- Good programmers have for decades maintained their own skeleton "template" programs for a variety of program types; simply load a template into a text editor and you've got a good start to the program...
- Legend has it that there's actually only been ONE program ever written in COBOL, and all programs ever "written" thereafter were simply derivatives of that one. Although this is clearly intended as a (probably) bad joke, it is nevertheless close to the very simple truth that many programmers "reuse" existing COBOL programs when creating new ones. There's certainly nothing preventing this from happening with programs written in other languages, but it does seem to happen more in COBOL shops. It's ironic that "code re-usability" is one of the arguments used to justify the existence of the "modern" languages.

2.1.5. Divisions Organize Programs

COBOL programs are structured into four major areas of coding, each with its own purpose. These four areas are known as divisions.

Each division may consist of a variety of sections and each section consists of one or more paragraphs. A paragraph consists of sentences, each of which consists of one or more statements.

This hierarchical structure of program components standardizes the composition of all COBOL programs. Much of this manual describes the various divisions, sections, paragraphs and statements that may comprise any COBOL program. COPY statement (see [COPY], page 59)

2.1.6. Copybooks

A *Copybook* is a segment of program code that may be utilized by multiple programs simply by having those programs use the COPY statement to import that code. This code may define files, data structures or procedural code.

Today's current programming languages have a statement (usually, this statement is named "import", "include" or "#include") that performs this same function. What makes the COBOL copybook feature different than the "include" facility in newer languages, however, is the fact that the COPY statement can edit the imported source code as it is being copied. This capability makes copybook libraries extremely valuable to making code reusable. Also see section 3. Compiler Directing Facility commands COPY and REPLACE.

2.1.7. Structured Data

A contiguous area of storage within the memory space of a program that may be referenced, by name, in a COBOL program is referred to as a *Data Item*. Other programming languages use the term variable, property or attribute to describe the same thing.

COBOL introduced the concept of structured data. The principle of structured data in COBOL is based on the idea of being able to group related and contiguously-allocated data items together into a single aggregate data item, called a *Group Item*. For example, a 35-character 'Employee-Name' group item might consist of a 20-character 'Last-Name' followed by a 14-character 'First-Name' and a 1-character 'Middle-Initial'.

A data item that isn't itself formed from other data items is referred to in COBOL as an *Elementary Item*. In the previous example, 'Last-Name', 'First-Name' and 'Middle-Initial' are all elementary items.

2.1.8. Files

One of COBOL's strengths is the wide variety of data files it is capable of accessing. GnuCOBOL programs, like those created with other COBOL implementations, need to have the structure of any files they will be reading and/or writing described to them. The highest-level characteristic of a file's structure is defined by specifying the organization of the file, as follows:

ORGANIZATION LINE SEQUENTIAL

These are files with the simplest of all internal structures. Their contents are structured simply as a series of identically- or differently-sized data records, each terminated by a special end-of-record delimiter character. An ASCII line-feed character (hexadecimal 0A) is the end-of-record delimiter character used by any UNIX or pseudo-UNIX (MinGW, Cygwin, OSX) GnuCOBOL build. A truly native Windows build would use a carriage-return, line-feed (hexadecimal 0D0A) sequence.

Records must be read from or written to these files in a purely sequential manner. The only way to read (or write) record number 100 would be to have read (or written) records number 1 through 99 first.

When the file is written to by a GnuCOBOL program, the delimiter sequence will be automatically appended to each data record as it is written to the file. A WRITE (see [WRITE], page 360) to this type of file will be done as if a BEFORE ADVANCING 1 LINE clause were specified on the WRITE, if no ADVANCING clause is coded.

When the file is read, the GnuCOBOL runtime system will strip the trailing delimiter sequence from each record. The data will be padded (on the right) with spaces if the data just read is shorter than the area described for data records in the program. If the data is too long, it will be truncated and the excess will be lost.

These files should not be defined to contain any exact binary data fields because the contents of those fields could inadvertently have the end-of-record sequence as part of their values — this would confuse the runtime system when reading the file, and it would interpret that value as an actual end-of-record sequence.

The following environment variables can have an effect on LINE SEQUENTIAL processing behaviour so may require changes to settings for:

COB_LS_FIXED COB_LS_NULLS COB_LS_SPLIT

When using Micro Focus compatable formats: COB-MF-LS-NULLS

COB_MF_LS_INSTAB

COB_MF_LS_SPLIT

COB_MF_LS_VALIDATE

See sections 10.2.3.4 and 10.2.3.7 for more information.

LINE ADVANCING

These are files with an internal structure similar to that of a line sequential file. These files are defined (without an explicit ORGANIZATION specification) using the LINE ADVANCING clause on their SELECT statement (see [SELECT], page 95).

When this kind of file is written to by a GnuCOBOL program, an end-of-record delimiter sequence will be automatically added to each data record as it is written to the file. A WRITE to this type of file will be done as if an AFTER ADVANCING 1 LINE clause were specified on the WRITE, if no ADVANCING clause is coded.

Like line sequential files, these files should not be defined to contain any exact binary data fields because the contents of those fields could inadvertently have the end-of-record sequence as part of their values — this would confuse the runtime system when reading the file, and it would interpret that value as an actual end-of-record sequence.

ORGANIZATION SEQUENTIAL

These files also have a simple internal structure. Their contents are structured simply as an arbitrarily-long sequence of data characters. This sequence of characters will be treated as a series of fixed-length records simply by logically splitting the sequence of characters up into fixed-length segments, each as long as the maximum record size defined in the program. There are no special end-of-record delimiter characters in the file and when the file is written to by a GnuCOBOL program, no delimiter sequence is appended to the data.

Records in this type of file are all the same physical length, except possibly for the very last record in the file, which may be shorter than the others. If variable-length

logical records are defined to the program, the space occupied by each physical record in the file will occupy the space described by the longest record description in the program.

So, if a file contains 1275 characters of data, and a program defines the structure of that file as containing 100-character records, then the file contents will consist of twelve (12) 100-character records with a final record containing only 75 characters. It would appear that it should be possible to locate and process any record in the file directly simply by calculating its starting character position based upon the program-defined record size. Even so, however, records must be still be read or written to these files in a purely sequential manner. The only way to read (or write) record number 100 would be to have read (or written) records number 1 through 99 first.

When the file is read, the data is transferred into the program exactly as it exists in the file. In the event that a short record is read as the very last record, that record will be padded (to the right) with spaces.

Care must be taken that programs reading such a file describe records whose length is exactly the same as that used by the program that created the file. For example, the following shows the contents of a SEQUENTIAL file created by a program that wrote five 6-character records to it. The 'A', 'B', . . . values reflect the records that were written to the file:

'AAAAAA'
'BBBBBB'
'CCCCCC'
'DDDDDD'
'EEEEEE'

Now, assume that another program reads this file, but describes 10-character records rather than 6. Here are the records that program will read:

'AAAAAABBBB' 'BBCCCCCCDD' 'DDDDEEEEEE'

There may be times where this is exactly what you were looking for. More often than not, however, this is not desirable behaviour. Suggestion: use a copybook to describe the record layouts of any file; this guarantees that multiple programs accessing that file will "see" the same record sizes and layouts by coding a COPY statement (see [COPY], page 59) to import the record layout(s) rather than hand-coding them.

These files *can* contain exact binary data fields. Because there is no character sequence that constitutes an end-of-record delimiter, the contents of record fields are irrelevant to the reading process.

ORGANIZATION RELATIVE

The contents of these files consist of a series of fixed-length data records prefixed with a four-byte record header. The record header contains the length of the data, in bytes. The byte-count does not include the four-byte record header.

Records in this type of file are all the same physical length. If variable-length logical records are defined to the program, the space occupied by each physical record in the file will occupy the maximum possible space, and the logical record length field will contain the number of bytes of data in the record that are actually in use.

This file organization was defined to accommodate either sequential or random processing. With a RELATIVE file, it is possible to read or write record 100 directly, without having to have first read or written records 1-99. The GnuCOBOL runtime

system uses the program-defined maximum record size to calculate a relative byte position in the file where the record header and data begin, and then transfers the necessary data to or from the program.

When the file is written by a GnuCOBOL program, no delimiter sequence is appended to the data, but a record-length field is added to the beginning of each physical record.

When the file is read, the data is transferred into the program exactly as it exists in the file.

Care must be taken that programs reading such a file describe records whose length is exactly the same as that used by the programs that created the file. It won't end well if the GnuCOBOL runtime library interprets a four-byte ASCII character string as a record length when it transfers data from the file into the program!

Suggestion: use a copybook to describe the record layouts of any file; this guarantees that multiple programs accessing that file will "see" the same record sizes and layouts by coding a COPY statement (see [COPY], page 59) to import the record layout(s) rather than hand-coding them.

These files can contain exact binary data fields. The contents of record fields are irrelevant to the reading process as there is no end-of-record delimiter.

ORGANIZATION INDEXED

This is the most advanced file structure available to GnuCOBOL programs. It's not possible to describe the physical structure of such files because that structure will vary depending upon which advanced file-management facility was included into the GnuCOBOL build you will be using (Berkeley Database [BDB], VBISAM, etc.). We will — instead — discuss the logical structure of the file.

There will be multiple structures stored for an INDEXED file. The first will be a data component, which may be thought of as being similar to the internal structure of a relative file. Data records may not, however, be directly accessed by their record number as would be the case with a relative file, nor may they be processed sequentially by their physical sequence in the file.

The remaining structures will be one or more index components. An index component is a data structure that (somehow) enables the contents of a field, called a primary key, within each data record (a customer number, an employee number, a product code, a name, etc.) to be converted to a record number so that the data record for any given primary key value can be directly read, written and/or deleted. Additionally, the index data structure is defined in such a manner as to allow the file to be processed sequentially, record-by-record, in ascending sequence of the primary key field values. Whether this index structure exists as a binary-searchable tree structure (b-tree), an elaborate hash structure or something else is pretty much irrelevant to the programmer — the behaviour of the structure will be as it was just described. The actual mechanism used will depend upon the advanced filemanagement package was included into your GnuCOBOL implementation when it was built.

The runtime system will not allow two records to be written to an indexed file with the same primary key value.

The capability exists for an additional field to be defined as what is known as an alternate key. Alternate key fields behave just like primary keys, allowing both direct and sequential access to record data based upon the alternate key field values, with one exception. That exception is the fact that alternate keys may be allowed to

have duplicate values, depending upon how the alternate key field is described to the GnuCOBOL compiler.

There may be any number of alternate keys, but each key field comes with a disk space penalty as well as an execution time penalty. As the number of alternate key fields increases, it will take longer and longer to write and/or modify records in the file.

These files can contain exact binary data fields. The contents of record fields are irrelevant to the reading process as there is no end-of-record delimiter.

All files are initially described to a GnuCOBOL program using a SELECT statement (see [SELECT], page 95). In addition to defining a name by which the file will be referenced within the program, the SELECT statement will specify the name and path by which the file will be known to the operating system along with its organization, locking and sharing attributes.

A file description in the FILE SECTION (see [FILE SECTION], page 112) will define the structure of records within the file, including whether or not variable-length records are possible and, if so, what the minimum and maximum length might be. In addition, the file description entry can specify file I/O block sizes.

2.1.9. Table Handling

Other programming languages have arrays; COBOL has tables. They're basically the same thing. There are two special statements that exist in the COBOL language — SEARCH and SEARCH ALL — that make finding data in a table easy.

SEARCH searches a table sequentially, stopping only when either a table entry matching one of any number of search conditions is found, or when all table entries have been checked against the search criteria and none matched any of those criteria.

SEARCH ALL performs an extremely fast search against a table sorted by a key field contained in each table entry. The algorithm used for such a search is a binary search. The algorithm ensures that only a small number of entries in the table need to be checked in order to find a desired entry or to determine that the desired entry doesn't exist in the table. The larger the table, the more effective this search becomes. For example, a binary search of a table containing 32,768 entries will locate a particular entry or determine the entry doesn't exist by looking at no more than fifteen (15) entries! The algorithm is explained in detail in the documentation of the SEARCH ALL statement (see [SEARCH ALL], page 328).

Finally, COBOL has the ability to perform in-place sorts of the data that is found in a table.

2.1.10. Sorting and Merging Data

The COBOL language includes a powerful SORT statement that can sort large amounts of data according to arbitrarily complex key structures. This data may originate from within the program or may be contained in one or more external files. The sorted data may be written automatically to one or more output files or may be processed, record-by-record in the sorted sequence.

A companion statement — MERGE — can combine the contents of multiple files together, provided those files are all pre-sorted in a similar manner according to the same key structure. The resulting output will consist of the contents of all of the input files, merged together and sequenced according to the common key structure(s). The output generated by a MERGE statement may be written automatically to one or more output files or may be processed internally by the program.

A special form of the SORT statement also exists just to sort the data that resides in a table. This is particularly useful if you wish to use SEARCH ALL against the table.

2.1.11. String Manipulation

There have been programming languages designed specifically for the processing of text strings, and there have been programming languages designed for the sole purpose of performing high-powered numerical computations. Most programming languages fall somewhere in the middle.

COBOL is no exception, although it does include some very powerful string manipulation capabilities; GnuCOBOL actually has even more string-manipulation capabilities than many other COBOL implementations. The following summarizes GnuCOBOL's string-processing capabilities:

Concatenate two or more strings

- CONCATENATE intrinsic function (see [CONCATENATE], page 372).
- STRING statement (see [STRING], page 347).

Conversion of a numeric time or date to a formatted character string

- LOCALE-TIME intrinsic function (see [LOCALE-TIME], page 404).
- LOCALE-DATE intrinsic function (see [LOCALE-DATE], page 403).

Convert a binary value to its corresponding character in the program's character set

• CHAR intrinsic function (see [CHAR], page 370). Add 1 to argument before invoking the function; the description of the CHAR intrinsic function presents a technique utilizing the MOVE statement that will accomplish the same thing without the need of adding 1 to the numeric argument value first.

Convert a character string to lower-case

- LOWER-CASE intrinsic function (see [LOWER-CASE], page 408).
- C\$TOLOWER built-in system subroutine (see [C\$TOLOWER], page 489).
- CBL_TOLOWER built-in system subroutine (see [CBL_TOLOWER], page 529).

Convert a character string to upper-case

- UPPER-CASE intrinsic function (see [UPPER-CASE], page 459).
- C\$TOUPPER built-in system subroutine (see [C\$TOUPPER], page 490).
- CBL_TOUPPER built-in system subroutine (see [CBL_TOUPPER], page 529).

Convert a character string to only printable characters

• C\$PRINTABLE built-in system subroutine (see [C\$PRINTABLE], page 487).

Convert a character to its numeric value in the program's character set

• ORD intrinsic function (see [ORD], page 431). Subtract 1 from the result; the description of the ORD intrinsic function presents a technique utilizing the MOVE statement that will accomplish the same thing without the need of adding 1 to the numeric argument value first.

Count occurrences of sub strings in a larger string

• INSPECT statement (see [INSPECT], page 297) with the TALLYING clause.

Decode a formatted numeric string back to a numeric value

- NUMVAL intrinsic function (see [NUMVAL], page 427).
- NUMVAL-C intrinsic function (see [NUMVAL-C], page 428).

Determine the length of a string or data-item capable of storing strings

- LENGTH intrinsic function (see [LENGTH], page 400).
- BYTE-LENGTH intrinsic function (see [BYTE-LENGTH], page 369).

Extract a sub string from a string based on its starting character position and length

• Use of a reference modifier on the string field - See [Reference Modifiers], page 37.

Format a numeric item for output, including thousands-separators (',' in the USA), currency symbols ('\$' in the USA), decimal points, credit/Debit Symbols, Leading Or Trailing Sign Characters

• MOVE statement (see [MOVE], page 305) with picture-symbol editing applied to the receiving field:

Justification (left, right or centred) of a string field

• C\$JUSTIFY built-in system subroutine (see [C\$JUSTIFY], page 483).

Monoalphabetic substitution of one or more characters in a string with different characters

- INSPECT statement (see [INSPECT], page 297) with the CONVERTING.
- TRANSFORM statement (see [TRANSFORM], page 354).
- SUBSTITUTE intrinsic function (see [SUBSTITUTE], page 448).
- SUBSTITUTE-CASE intrinsic function (see [SUBSTITUTE-CASE], page 449).

Parse a string, breaking it up into sub strings based upon one or more delimiting character sequences¹

• UNSTRING statement (see [UNSTRING], page 356).

Removal of leading or trailing spaces from a string

• TRIM intrinsic function (see [TRIM], page 458).

Substitution of a single sub string with another of the same length, based upon the sub strings starting character position and length

• MOVE statement (see [MOVE], page 305) with a reference modifier on the "receiving" field (see [Reference Modifiers], page 37).

Substitution of one or more sub strings in a string with replacement sub strings of the same length, regardless of where they occur

- INSPECT statement (see [INSPECT], page 297) with a REPLACING clause.
- SUBSTITUTE intrinsic function (see [SUBSTITUTE], page 448).
- SUBSTITUTE-CASE intrinsic function (see [SUBSTITUTE-CASE], page 449).

Substitution of one or more sub strings in a string with replacement sub strings of a potentially different length, regardless of where they occur

- SUBSTITUTE intrinsic function (see [SUBSTITUTE], page 448).
- SUBSTITUTE-CASE intrinsic function (see [SUBSTITUTE-CASE], page 449).

2.1.12. Screen Formatting Features

The COBOL2002 standard formalizes extensions to the COBOL language that allow for the definition and processing of text-based screens, as is a typical function on mainframe and mid-frame computers as well as on many point-of-sale (i.e. "cash register") systems. GnuCOBOL implements virtually all the screen-handling features described by COBOL2002.

These features allow fields to be displayed at specific row/column positions, various colors and video attributes to be assigned to screen fields and the pressing of specific function keys (F1, F2, ...) to be detectable. All of this takes place through the auspices of the SCREEN SECTION (see [SCREEN SECTION], page 131) and special formats of the ACCEPT statement (see [ACCEPT], page 230) and the DISPLAY statement (see [DISPLAY], page 263).

¹ These delimiters may be single characters, multiple-character strings or multiple consecutive occurrences of either

The COBOL2002 standard, and therefore GnuCOBOL, only covers textual user interface (TUI) screens (those comprised of ASCII characters presented using a variety of visual attributes) and not the more-advanced graphical user interface (GUI) screen design and processing capabilities built into most modern operating systems. There are subroutine-based packages available that can do full GUI presentation — most of which may be called by GnuCOBOL programs, with a moderate research time investment (Tcl/Tk, for example) — but none are currently included with GnuCOBOL.

2.1.12.1. A Sample Screen

A Sample Screen Produced by a GnuCOBOL Program:



The above screen was produced by the GnuCOBOL Interactive Compiler, or GCic. See Section "GCic" in *GnuCOBOL Sample Programs*, for the source and cross-reference listing of this program.

Screens are defined in the screen section of the data division. Once defined, screens are used at run-time via the ACCEPT and DISPLAY statements.

2.1.12.2. Color Palette and Video Attributes

GnuCOBOL supports the following visual attribute specifications in the SCREEN SECTION (see [SCREEN SECTION], page 131):

Color

Eight (8) different colors may be specified for both the background (screen) and foreground (text) color of any row/column position on the screen. Colors are specified by number, although a copybook supplied with all GnuCOBOL distributions (screenio.cpy) defines COB-COLOR-xxxxxx names for the various colors so they may be specified as a more meaningful name rather than a number. The eight colors, by number, with the constant names defined in screenio.cpy, are as follows:

Black COB-COLOR-BLACK

Blue COB-COLOR-BLUE

Green COB-COLOR-GREEN

Cyan COB-COLOR-CYAN

Red COB-COLOR-RED

Magenta COB-COLOR-MAGENTA

Yellow COB-COLOR-YELLOW

White COB-COLOR-WHITE

Text Brightness

There are three possible brightness levels supported for text — lowlight (dim), normal and highlight (bright). Not all GnuCOBOL implementations will support all three (some treat lowlight the same as normal). The deciding factor as to whether two or three levels are supported lies with the version of the *curses* package that is being used. This is a utility screen-IO package that is included into the GnuCOBOL run-time library when the GnuCOBOL software is built.

As a general rule of thumb, Windows implementations support two levels while Unix ones support all three.

Blinking

This too is a video feature that is dependent upon the *curses* package built into your version of GnuCOBOL. If blinking is enabled in that package, text displayed in fields defined in the screen section as being blinking will endlessly cycle between the brightest possible setting (highlight) and an "invisible" setting where the text color matches that of the field background color. A Windows build, which generally uses the "pcurses" package, will uses a brighter-than-normal background color to signify "blinking".

Reverse Video

This video attribute simply swaps the foreground and background colors and display options.

Field Outlining

It is possible, if supported by the *curses* package being used, to draw borders on the top, left and/or bottom edges of a field.


Secure Input

If desired, screen fields used as input fields may defined as "secure" fields, where each input character (regardless of what was actually typed) will appear as an asterisk (*) character. The actual character whose key was pressed will still be stored into the field in the program, however. This is very useful for password or account number fields.

Prompt Character

Input fields may have any character used as a fill character. These fill characters provide a visual indication of the size of the input field, and will automatically be transformed into spaces when the input field is processed by the program. If no such character is defined for an input field, an underscore ('_') will be assumed.

The following is a sample of the GnuCOBOL color Palette, showing all possible combinations of the various video attributes. This example was prepared on a Macintosh running OSX Mavericks (10.9). Blinking works — the screen snapshot shows things in mid blink, when the text and background colors are momentarily the same. Unfortunately, only two screen intensities are available (like Windows, the "lowlight" setting is the same as the default).



The GnuCOBOL Color Palette and Video Options::

The rows of each block are numbered with the background color while columns are numbered with the foreground color.

See Section "Colors" in *GnuCOBOL Sample Programs*, for a source and cross-reference listing of the program (Colors.cbl) that produced the above screen.

2.1.13. Report Writer Features

GnuCOBOL includes an implementation of the Report Writer Control System, or RWCS. The reportwriter module is now fully implemented as of version 3.0. This is a standardized, optional add-on feature to the COBOL language which automates much of the mechanics involved in the generation of printed reports by:

- 1. Controlling the pagination of reports, including:
 - A. The automatic production of a one-time notice on the first page of the report (report heading).
 - B. The production of zero or more header lines at the top of every page of the report (page heading).
 - C. The production of zero or more footer lines at the bottom of every page of the report (page footing).
 - D. The automatic numbering of printed pages.
 - E. The formatting of those report lines that make up the main body of the report (detail).
 - F. Full awareness of where the "pen" is about to "write" on the current page, automatically forcing an eject to a new page, along with the automatic generation of a page footer to close the old page and/or a page header to begin the new one.
 - G. The production of a one-time notice at the end of the last page of a report (report footing).

- 2. Performing special reporting actions based upon the fact that the data being used to generate the report has been sorted according to one or more key fields:
 - A. Automatically suppressing the presentation of one or more fields of data from the detail group when the value(s) of the field(s) duplicate those of the previously generated detail group. Fields such as these are referred to as group-indicate fields.
 - B. Automatically causing suppressed detail group-indicate fields to re-appear should a detail group be printed on a new page.
 - C. Recognizing when control fields on the report fields tied to those that were used as SORT statement (see [SORT], page 339) keys have changed. This is known as a control break. The RWCS can automatically perform the following reporting actions when a control break occurs:
 - Producing a footer, known as a control footing after the detail lines that shared the same old value for the control field.
 - Producing a header, known as a control heading before the detail lines that share the same new value for the control field.
- 3. Perform data summarise, as follows:
 - A. Automatically generating subtotals in control and/or report footings, summarizing values of any fields in the detail group.
 - B. Automatically generating crossfoot totals in detail groups. These would be sums of two or more values presented in the detail group.

The REPORT SECTION (see [REPORT SECTION], page 124) documentation explores the description of reports and the PROCEDURE DIVISION (see [PROCEDURE DIVISION], page 211) chapter documents the various language statements that actually produce reports. Before reading these, you might find it helpful to read [Report Writer Usage], page 537, which is dedicated to putting the pieces together for you.

2.1.14. Data Initialization

There are three ways in which data division data gets initialized.

- 1. When a program or subprogram is first executed, much of the data in its data division will be initialized as follows:
 - Alphanumeric and alphabetic (i.e. text) data items will be initialized to SPACES.
 - Numeric data items will be initialized to a value of ZERO.
 - Data items with an explicit VALUE (see [VALUE], page 207) clause in their definition will be initialized to that specific value.

The various sections of the data division each have their own rules as to when the actions described above will occur — consult the documentation on those sections for additional information.

These default initialization rules can vary quite substantially from one COBOL implementation to another. For example, it is quite common for data division storage to be initialized to all binary zeros except for those data items where VALUE clauses are present. Take care when working with applications originally developed for another COBOL implementation to ensure that GnuCOBOL's default initialization rules won't prove disruptive.

2. A programmer may use the INITIALIZE statement (see [INITIALIZE], page 292) to initialise any group or elementary data item at any time. This statement provides far more initialization options than just the simple rules stated above.

3. When the ALLOCATE statement (see [ALLOCATE], page 250) statement is used to allocate a data item or to simply allocate an area of storage of a size specified on the ALLOCATE, that allocation may occur with or without initialization, as per the programmer's needs.

2.1.15. Syntax Diagram Conventions

Syntax of the GnuCOBOL language will be described in special *syntax diagrams* using the following syntactical-description techniques:

MANDATORY-RESERVED-WORD

Reserved words of the COBOL language will appear in UPPER-CASE. When they appear underlined, as this one is, they are required reserved words.

OPTIONAL-RESERVED-WORD

When reserved words appear without underlining, as this one is, they are optional; such reserved words are available in the language syntax merely to improve readability — their presence or absence has no effect upon the program.

ABBREVIATION

ADDILL VIALIO

When only a portion of a reserved word is underlined, it indicates that the word may either be coded in its full form or may be abbreviated to the portion that is underlined.

substitutable-items

Generic terms representing user-defined substitutable items will be shown entirely in lower-case in syntax diagrams. When such items are referenced in text, they will appear as *substitutable-items*.

Complex-Syntax-Clause

Items appearing in Mixed Case within a syntax diagram represent complex clauses of other syntax elements that may appear in that position. Some COBOL syntax gets quite complicated, and using a convention such as this significantly reduces the complexity of a syntax diagram. When such items are referenced in text, they will appear as *Complex-Syntax-Clause*.

- [] Square bracket meta characters on syntax diagrams document language syntax that is optional. The [] characters themselves should not be coded. If a syntax diagram contains 'a [b] c', the 'a' and 'c' syntax elements are mandatory but the 'b' element is optional.
- Vertical bar meta characters on syntax diagrams document simple choices. The l character itself should not be coded. If a syntax diagram contains 'a|b|c', exactly one of the items 'a', 'b' or 'c' must be selected.

```
{ xxxxxx } 
{ yyyyyy } 
{ zzzzzz }
```

A vertical list of items, bounded by multiple brace characters, is another way of signifying a choice between a series of items where exactly one item must be selected. This form is used to show choices when one or more of the selections is more complex than just a single word, or when there are too many choices to present horizontally with '|' meta characters.

| xxxxxx | | yyyyyy | | zzzzz |

A vertical list of items, bounded by multiple vertical bar characters, signifies a choice between a series of items where one *or more* of the choices could be selected.

- The ... meta character sequence signifies that the syntax element immediately preceding it may be repeated. The ... sequence itself should not be coded. If a syntax diagram contains a b... c, syntax element 'a' must be followed by at least one 'b' element (possibly more) and the entire sequence must be terminated by a 'c' syntax element.
- The braces ('{' and '}') meta characters may be used to group a sequence of syntax elements together so that they may be treated as a single entity. The {} characters themselves should not be coded. These are typically used in combination with the '|' or '...' meta characters.

\$*^()-+=:"'<,>./

Any of these characters appearing within a syntax diagram are to be interpreted literally, and are characters that must be coded — where allowed — in the statement whose format is being described. Note that a '.' character is a literal character that must be coded on a statement whereas a '...' symbol is the meta character sequence described above.

2.1.16. Format of Program Source Lines

Prior to the COBOL2002 standard, source statements in COBOL programs were structured around 80-column punched cards. This means that each source line in a COBOL program consisted of five different "areas", defined by their column number(s).

As of the COBOL2002 standard, a second mode now exists for COBOL source code statements — in this mode of operation, COBOL statements may each be up to 255 characters long, with no specific requirements as to what should appear in which columns.

Of course, in keeping with the long-standing COBOL tradition of maintaining backwards compatibility with older standards, programmers (and, of course, compliant COBOL compilers) are capable of working in either mode. It is even possible to switch back and forth in the same program. The terms Fixed Format Mode and Free Format Mode are used to refer to these two modes of source code formatting.

The GnuCOBOL compiler (cobc) supports both of these source line format modes, defaulting to Fixed Format Mode lacking any other information.

The compiler can be instructed to operate in either mode in any of the following four ways:

- 1. Using a compiler option switch use the —fixed switch to start in Fixed Format Mode (remember that this is the default) or the —free switch to start in Free Format Mode.
- 2. You may use the SOURCEFORMAT AS FIXED and SOURCEFORMAT AS FREE clauses of the >>SET CDF directive (see [>>SET], page 66) within your source code to switch to Fixed or Free Format Mode, respectively.
- 3. You may use the >>FORMAT IS FIXED and FORMAT IS FREE clauses of the >>DEFINE CDF directive (see [>>DEFINE], page 63) within your source code to switch to Fixed or Free Format Mode, respectively.
- 4. You may use the >>SOURCE CDF directive (see [>>SOURCE], page 67) to switch to Free Format Mode (>>SOURCE FORMAT IS FREE) or Fixed Format Mode (>>SOURCE FORMAT IS FIXED.

Using methods 2-4 above, you may switch back and forth between the two formats at will.

The last three options above are all equivalent; all three are supported by GnuCOBOL so that source code compatibility may be maintained with a wide variety of other COBOL implementations. With all three, if the compiler is *currently* in Fixed Format Mode, the >> must begin in column 8 or beyond, provided no part of the directive extends past column 72. If the compiler is currently in Free Format Mode, the >> may appear in any column, provided no part of the directive extends past column 255.

Depending upon which source format mode the compiler is in, you will need to follow various rules for the format mode currently in effect. These rules are presented in the upcoming paragraphs.

The following discussion presents the various components of every GnuCOBOL source line record when the compiler is operating in Fixed Format Mode. Remember that this is the default mode for the GnuCOBOL compiler.

1-6 Sequence Number Area

Historically, back in the days when punched-cards were used to submit COBOL program source to a COBOL compiler, this part of a COBOL statement was reserved for a six-digit sequence number. While the contents of this area are ignored by COBOL compilers, it existed so that a program actually punched on 80-character cards could — if the card deck were dropped on the floor — be run through a card sorter machine and restored to its proper sequence. Of course, this isn't necessary today; if truth be told, it hasn't been necessary for a long time.

See [Marking Changes in Programs], page 621, for discussion of a valuable use to which the sequence number area may be put today.

7 Indicator Area

Column 7 serves as an indicator in which one of five possible values will appear — space, D (or d), - (dash), / or *. The meanings of these characters are as follows:

space No special meaning — this is the normal character that will appear in this area.

D/d The line contains a valid GnuCOBOL statement that is normally treated as a comment unless the program is being compiled in debugging mode.

* The line is a comment.

/ The line is a comment that will also force a page eject in the compilation listing. While GnuCOBOL will honour such a line as a comment, it will not form-feed any generated listing.

The line is a continuation of the previous line. These are needed only when an alphanumeric literal (quoted character string), reserved word or user-defined word are being split across lines.

8-11 Area A

Language DIVISION, SECTION and paragraph section headers must begin in Area A, as must the level numbers 01, 77 in data description entries and the FD and SD file and SORT description headers.

12-72 Area B

All other COBOL programming language components are coded in these columns.

73-80 Program Name Area

This is another obsolete area of COBOL statements. This part of every statement also hails back to the day when programs were punched on cards; it was expected that the name of the program (or at least the first 8 characters of it) would be punched here so that — if a dropped COBOL source deck contained more than one program — that handy card sorter machine could be used to first separate the cards by program name and then sort them by sequence number. Today's COBOL compilers (including GnuCOBOL) simply ignore anything past column 72.

See [Marking Changes in Programs], page 621, for discussion of a valuable use to which the program name area may be put today.

2.1.17. Program Structure

Complete GnuCOBOL Program Syntax

```
[ IDENTIFICATION DIVISION. ]
  PROGRAM-ID|FUNCTION-ID. name-1 [ Program-Options ] .
  [ ENVIRONMENT DIVISION. ]
[ CONFIGURATION SECTION. ]
  [ SOURCE-COMPUTER.
                        Compilation-Computer-Specification . ]
[ OBJECT-COMPUTER.
                        Execution-Computer-Specification . ]
[ REPOSITORY.
                        Function-Specification... . ]
 ~~~~~~~~~
[ SPECIAL-NAMES.
                        Program-Configuration-Specification . ]
[ INPUT-OUTPUT SECTION. ]
[ FILE-CONTROL.
                        General-File-Description... ]
[ I-O-CONTROL.
                        File-Buffering-Specification... ]
[ DATA DIVISION. ]
 ~~~~~~~~~~~~
[ FILE SECTION.
                        Detailed-File-Description... ]
 ~~~~~~~~~~~
[ WORKING-STORAGE SECTION. Permanent-Data-Definition... ]
[ LOCAL-STORAGE SECTION.
                        Temporary-Data-Definition... ]
  [ LINKAGE SECTION.
                        Subprogram-Argument-Description... ]
[ REPORT SECTION.
                        Report-Description... . ]
[ SCREEN SECTION.
                        Screen-Layout-Definition... . ]
 ~~~~~ ~~~~~
 PROCEDURE DIVISION [ { USING Subprogram-Argument...
                                                      } ]
                    { CHAINING Main-Program-Argument... }
                     RETURNING identifier-1].
[ DECLARATIVES. ]
[ Event-Handler-Routine... . ]
[ END DECLARATIVES. ]
```

```
General-Program-Logic
[Nested-Subprogram...]
[END PROGRAM|FUNCTION name-1]
```

Each program consists of up to four *Divisions* (major groupings of sections, paragraphs and descriptive or procedural coding that all relate to a common purpose), named Identification, Environment, Data and Procedure.

- 1. Not all divisions are needed in every program, but they must be specified in the order shown when they are used.
- 2. The following points pertain to the identification division
 - The IDENTIFICATION DIVISION. header is always optional.
- 3. The following points pertain to the environment division:
 - If both optional sections of this division are coded, they must be coded in the sequence shown.
 - Each of these sections consists of a series of specific paragraphs (SOURCE-COMPUTER and OBJECT-COMPUTER, for example). Each of these paragraphs serves a specific purpose. If no code is required for the purpose one of the paragraphs serves, the entire paragraph may be omitted.
 - If none of the paragraphs within one of the sections are coded, the section header itself may be omitted.
 - The paragraphs within each section may only be coded in that section, but may be coded in any order.
 - If none of the sections within the environment division are coded, the ENVIRONMENT DIVISION. header itself may be omitted.
- 4. The following points pertain to the data division:
 - The data division consists of six optional sections when used, those sections must be coded in the order shown in the syntax diagram.
 - Each of these sections consists of code which serves a specific purpose. If no code is required for the purpose one of those sections serves, the entire section, including its header, may be omitted.
 - If none of the sections within the data division are coded (a highly unlikely, but theoretically possible circumstance), the DATA DIVISION. header itself may be omitted.
- 5. The following points pertain to the procedure division:
 - As with the other divisions, the procedure division may consist of sections and those sections may in turn consist of paragraphs. Unlike the other divisions, however, section and paragraph names are defined by the programmer, and there may not be any defined at all if the programmer so wishes.
 - Each Event-Handler-Routine will be a separate section devoted to trapping a particular run-time event. If there are no such sections coded, the DECLARATIVES. and END DECLARATIVES. lines may be omitted.
- 6. A single file of COBOL source code may contain:
 - A portion of a program; these files are known as copybooks
 - A single program. In this case, the END PROGRAM or END FUNCTION statement is optional.

- Multiple programs, separated from one another by END PROGRAM or END FUNCTION statements. The final program in such a source code file need not have an END PROGRAM or END FUNCTION statement.
- 7. Subprogram 'B' may be nested inside program 'A' by including program B's source code at the end of program A's procedure division without an intervening END PROGRAM A. or END FUNCTION A. statement. For now, that's all that will be said about nesting. See [Independent vs Contained vs Nested Subprograms], page 603, for more information.
- 8. Regardless of how many programs comprise a single GnuCOBOL source file, only a single output executable program will be generated from that source file when the file is compiled.

2.1.18. Comments

The following information describes how comments may be embedded into GnuCOBOL program source to provide documentation.

Comment	Type	Source	Mode —	Description
Comment	TAbe	Source	mode —	Description

Blank Lines FIXED — Blank lines may be inserted as desired.

FREE — Blank lines may be inserted as desired.

Full-line comments

FIXED — An entire source line will be treated as a comment (and will be ignored by the compiler) by coding an asterisk ('*') in column seven (7).

FREE — An entire source line will be treated as a comment (and will be ignored by the compiler) by coding the sequence '*>', starting in any column, as the first non-blank characters on the

Full-line comments with form-feed

FIXED — An entire source line will be treated as a comment by coding a slash ('/') in column seven (7). Many COBOL compilers will also issue a form-feed in the program listing so that the '/' line is at the top of a new page. The GnuCOBOL compiler does not support this form-feed behaviour.

The GnuCOBOL Interactive Compiler, or GCic, does support this form-feed behaviour when it generates program source listings! See Section "GCic" in *GnuCOBOL Sample Programs*, for the source and cross-reference listing (produced by GCic) of this program — you can see the effect of '/' there.

FREE — There is no Free Source Mode equivalent to '/'.

Partial-line comments

FIXED — Any text following the character sequence '*>' on a source line will be treated as a comment. The '*' must appear in column seven (7) or beyond.

FREE — Any text following the character sequence '*>' on a source line will be treated as a comment. The '*' may appear in any column.

Comments that may be treated as code, typically for debugging purposes **FIXED** — By coding a 'D' in column 7 (upper- or lower-case), an otherwise valid GnuCOBOL source line will be treated as a comment by the compiler.

FREE — By specifying the character sequence '>>D' (upper-or lower-case) as the first non-blank characters on a source line, an otherwise valid GnuCOBOL source line will be treated as a comment by the compiler.

Debugging statements may be compiled either by specifying the -fdebugging-line switch on the GnuCOBOL compiler or by adding the WITH DEBUGGING MODE clause to the SOURCE-COMPUTER paragraph.

2.1.19. Literals

Literals are constant values that will not change during the execution of a program. There are two fundamental types of literals — numeric and alphanumeric.

2.1.19.1. Numeric Literals

A numeric literal

- Integers such as 1, 56, 2192 or -54.
- Non-integer fixed point values such as 1.317 or -2.95.
- Floating-point values using 'Enn' notation such as 9.92E25, representing 9.92 x 10^{25} (10 raised to the 25th power) or 5.7E-14, representing 5.7 x 10^{-14} (10 raised to the -14th power). Both the mantissa (the number before the 'E') and the exponent (the number after the 'E') may be explicitly specified as positive (with a '+'), negative (with a '-') or unsigned (and therefore implicitly positive). A floating-point literals value must be within the range $-1.7 \ x \ 10^{308} \ \text{to} +1.7 \ x \ 10^{308} \ \text{with no more than 15 decimal digits of precision.}$
- Hexadecimal numeric literals
- Null terminated literals
- Raw C string using L"characters".
- Binary using B#0 or 1.
- Octal using O#0 7. (That is the letter '0').
- Hexadecimal number using H# or X# '0' 'F'.
- Boolean Literals (Standard) B" character ".
- Boolean Literals (Hexadecimal) BX" hex character ".
- National Literals (Standard) N" character " or NC" character ".
- National Literals (Hexadecimal) NX" character ".

2.1.19.2. Alphanumeric Literals

An alphanumeric literal

An alphanumeric literal is not valid for use in arithmetic expressions unless it is first converted to its numeric computational equivalent; there are three numeric conversion intrinsic functions built into GnuCOBOL that can perform this conversion — NUMVAL (see [NUMVAL], page 427), NUMVAL-C (see [NUMVAL-C], page 428) and NUMVAL-F (see [NUMVAL-F], page 430).

Alphanumeric literals may take any of the following forms:

• A sequence of characters enclosed by a pair of single-quote (',')

- A literal formed according to the same rules as for a string literal (above), but prefixed with the letter 'Z' (upper- or lower-case) constitutes a zero-delimited string literal. These literals differ from ordinary string literals in that they will be explicitly terminated with a byte of hexadecimal value 00. These Zero-Delimited Alphanumeric Literals
- A Hexadecimal Alphanumeric Literal

Alphanumeric literals too long to fit on a single line may be continued to the next line in one of two ways:

1. If you are using Fixed Format Mode, the alphanumeric literal can be run right up to and including column 72. The literal may then be continued on the next line anywhere after column 11 by coding another quote or apostrophe (whichever was used to begin the literal originally). The continuation line must also have a hyphen (-)

```
1 2 3 4 5 6 7
123456789012345678901234567890123456789012345678901234567890123
```

```
O1 LONG-LITERAL-VALUE-DEMO PIC X(60) VALUE "This is a long 1 "ong literal that " must be continu "ed.".
```

2. Regardless of whether the compiler is operating in Fixed or Free Format Mode, GnuCOBOL allows alphanumeric literals to be broken up into separate fragments. These fragments have their own beginning and ending quote/apostrophe characters and are "glued together" at compilation time using '&'

```
O1 LONG-LITERAL-VALUE-DEMO PIC X(60) VALUE "This is a" & "long literal that must " & "be continued.".
```

If your program is using Free Format Mode, there's less need to continue long alphanumeric literals because statements may be as long as 255 characters.

Numeric literals may be split across lines just as alphanumeric literals are, using either of the above techniques and both reserved and user-defined words can be split across lines too (using the first technique). The continuation of numeric literals and user-defined/reserved words is provided merely to provide compatibility with older COBOL versions and programs, but should not be used with new programs — it just makes for ugly-looking programs.

2.1.19.3. Figurative Constants

Figurative constants are reserved words that may be used as literals anywhere the figurative constants value could be interpreted as an arbitrarily long sequence of the characters in question. When a specific length is required, such as would be the case with an argument to a subprogram, a figurative constant may not be used. Thus, the following are valid uses of figurative constants:

```
05 FILLER PIC 9(10) VALUE ZEROS.
...
MOVE SPACES TO Employee-Name
But this is not:
```

```
CALL "SUBPGM" USING SPACES
```

The following are the GnuCOBOL figurative constants and their respective equivalent values.

ZERO This figurative constant has a value of numeric 0 (zero). ZEROS and ZEROES are both synonyms of ZERO.

SPACE This figurative constant has a value of one or more space characters. SPACES is a synonym of SPACE.

QUOTE This figurative constant has a value of one or more double-quote characters ("). QUOTES is a synonym of QUOTE.

LOW-VALUE

This figurative constant has a value of one or more of whatever character occupies the lowest position in the program's collating sequence as defined in the <code>OBJECT-COMPUTER</code> (see <code>[OBJECT-COMPUTER]</code>, page 82) paragraph or — if no such specification was made — in whatever default character set the program is using (typically, this is the ASCII character set). <code>LOW-VALUES</code> is a synonym of <code>LOW-VALUE</code>.

When the character set in use is ASCII with no collating sequence modifications, the LOW-VALUES figurative constant value is the ASCII NUL character. Because character sets can be redefined, however, you should not rely on this fact. Use the NULL figurative constant instead.

HIGH-VALUE

This figurative constant has a value of one or more of whatever character occupies the highest position in the program's collating sequence as defined in the OBJECT-COMPUTER paragraph or — if no such specification was made — in whatever default character set the program is using (typically, this is the ASCII character set). HIGH-VALUES is a synonym of HIGH-VALUE.

NULL A character comprised entirely of zero-bits (regardless of the programs collating sequence).

Programmers may create their own figurative constants via the SYMBOLIC CHARACTERS (see [Symbolic-Characters-Clause], page 92) clause of the SPECIAL-NAMES (see [SPECIAL-NAMES], page 84) paragraph.

2.1.20. Punctuation

A comma (',')

The use of comma characters can cause confusion to a COBOL compiler if the DECIMAL POINT IS COMMA clause is used in the SPECIAL-NAMES (see [SPECIAL-NAMES], page 84) paragraph, as might be the case in Europe. The following statement, which calls a subroutine passing it two arguments (the numeric constants 1 and 2):

CALL "SUBROUTINE" USING 1,2

Would — with DECIMAL POINT IS COMMA in effect — actually be interpreted as a subroutine call with 1 argument (the non-integer numeric literal whose value is 1 and 2 tenths). For this reason, it is best to always follow a comma with a space.

The period character ('.')

The rules for where and when periods are needed in the procedure division are somewhat complicated. See [Use of Periods], page 49, for the details.

2.1.21. Interfacing to Other Environments

Through the CALL statement, COBOL programs may invoke other COBOL programs serving as subprograms. This is quite similar to cross-program linkage capabilities provided by other languages. In GnuCOBOL's case, the CALL facility is powerful enough to be tailored to the point where a GnuCOBOL program can communicate with operating system, database management and run-time library APIs, even if they weren't written in COBOL themselves. See [GnuCOBOL

Main Programs CALLing C Subprograms], page 616, for an example of how a GnuCOBOL program could invoke a C-language subprogram, passing information back and forth between the two.

The fact that GnuCOBOL supports a full-featured two-way interface with C-language programs means that — even if you cannot access a library API directly — you could always do so via a small C "wrapper" program that is CALLed by a GnuCOBOL program.

2.2. The COBOL Language - Advanced Techniques

2.2.1. Table References

COBOL uses parenthesis to specify the subscripts used to reference table entries (tables in COBOL are what other programming languages refer to as arrays).

For example, observe the following data structure which defines a 4 column by 3 row grid of characters:

```
01 GRID.
05 GRID-ROW OCCURS 3 TIMES.
10 GRID-COLUMN OCCURS 4 TIMES.
15 GRID-CHARACTER PIC X(1).
```

If the structure contains the following grid of characters:

A B C D E F G H I J K L

Then GRID-CHARACTER (2, 3) references the 'G' and GRID-CHARACTER (3, 2) references the 'J'.

Subscripts may be specified as numeric (integer) literals, numeric (integer) data items, data items created with any of the picture-less integer USAGE (see [USAGE], page 198) specifications, USAGE INDEX data items or arithmetic expressions resulting in a non-zero integer value.

In the above examples, a comma is used as a separator character between the two subscript values; semicolons (;) are also valid subscript separator characters, as are spaces! The use of a comma or semicolon separator in such a situation is technically optional, but by convention most COBOL programmers use one or the other. The use of no separator character (other than a space) is not recommended, even though it is syntactically correct, as this practice can lead to programmer-unfriendly code. It isn't too difficult to read and understand GRID-CHARACTER(23), but it's another story entirely when trying to comprehend GRID-CHARACTER(I+1J/3) (instead of GRID-CHARACTER(I+1J/3)). The compiler accepts it, but too much of this would make my head hurt.

2.2.2. Qualification of Data Names

COBOL allows data names to be duplicated within a program, provided references to those data names may be made in such a manner as to make those references unique through a process known as qualification.

To see qualification at work, observe the following segments of two data records defined in a COBOL program:

```
01 EMPLOYEE.
                                 01 CUSTOMER.
   05 MAILING-ADDRESS.
                                     05 MAILING-ADDRESS.
       10 STREET
                       PIC X(35).
                                        10 STREET
                                                        PIC X(35).
       10 CITY
                       PIC X(15).
                                        10 CITY
                                                         PIC X(15).
       10 STATE
                       PIC X(2).
                                        10 STATE
                                                        PIC X(2).
       10 ZIP-CODE.
                                        10 ZIP-CODE.
          15 ZIP-CODE-5 PIC 9(5).
                                           15 ZIP-CODE-5 PIC 9(5).
                       PIC X(4).
          15 FILLER
                                           15 FILLER
                                                         PIC X(4).
```

Now, let's deal with the problem of setting the CITY portion of an EMPLOYEES MAILING-ADDRESS to 'Philadelphia'. Clearly, MOVE 'Philadelphia' TO CITY cannot work because the compiler will be unable to determine which of the two CITY fields you are referring to.

In an attempt to correct the problem, we could qualify the reference to CITY as MOVE 'Philadelphia' TO CITY OF MAILING-ADDRESS.

Unfortunately that too is insufficient because it still insufficiently specifies which CITY is being referenced. To truly identify which specific CITY you want, you'd have to code MOVE 'Philadelphia' TO CITY OF MAILING-ADDRESS OF EMPLOYEE.

Now there can be no confusion as to which CITY is being changed. Fortunately, you don't need to be quite so specific; COBOL allows intermediate and unnecessary qualification levels to be omitted. This allows MOVE 'Philadelphia' TO CITY OF EMPLOYEE to do the job nicely.

If you need to qualify a reference to a table, do so by coding something like identifier-1 OF identifier-2 (subscript(s)).

The reserved word IN may be used in lieu of OF.

2.2.3. Reference Modifiers

Reference Modifier (Format 1) Syntax identifier-1 [OF|IN identifier-2] [(subscript...)] (start:[length])

Reference Modifier (Format 2) Syntax

intrinsic-function-reference (start:[length])

The COBOL 1985 standard introduced the concept of a reference modifier to facilitate references to only a portion of a data item; GnuCOBOL fully supports reference modification.

The *start* value indicates the starting character position being referenced (character position values start with 1, not 0 as is the case in some programming languages) and *length* specifies how many characters are wanted.

If no *length* is specified, a value equivalent to the remaining character positions from *start* to the end of *identifier-1* or to the end of the value returned by the function will be assumed.

Both start and length may be specified as integer numeric literals, integer numeric data items or arithmetic expressions with an integer value.

Here are a few examples:

CUSTOMER-LAST-NAME (1:3)

References the first three characters of CUSTOMER-LAST-NAME.

CUSTOMER-LAST-NAME (4:)

References all character positions of CUSTOMER-LAST-NAME from the fourth onward.

FUNCTION CURRENT-DATE (5:2)

References the current month as a 2-digit number in character form. See [CURRENT-DATE], page 375, for more information.

Hex-Digits (Nibble + 1:1)

Assuming that Nibble is a numeric data item with a value in the range 0-15, and Hex-Digits is a PIC X(16) item with a value of 0123456789ABCDEF, this converts that numeric value to a hexadecimal digit.

Table-Entry (6) (7:5)

References characters 7 through 11 (5 characters in total) in the 6th occurrence of Table-Entry.

Reference modification may be used anywhere an identifier is legal, including serving as the receiving field of statements like MOVE (see [MOVE], page 305), STRING (see [STRING], page 347) and ACCEPT (see [ACCEPT], page 230), to name a few.

2.2.4. Arithmetic Expressions

Arithmetic-Expression Syntax

Unary-Expression Syntax

Arithmetic expressions are formed using four categories of operations — exponentiation, multiplication & division, addition & subtraction, and sign specification.

In complex expressions composed of multiple operators and operands, a precedence of operation applies whereby those operations having a higher precedence are computed first before operations with a lower precedence.

As is the case in almost any other programming language, the programmer is always free to use pairs of parenthesis to enclose sub-expressions of complex expressions that are to be evaluated before other sub-expressions rather than let operator precedence dictate the sequence of evaluation.

In highest to lowest order of precedence, here is a discussion of each category of operation:

Level 1 (Highest) — Unary Sign Specification (+ and - with a single argument)

The unary "minus" (-) operator returns the arithmetic negation of its single argument, effectively returning as its value the product of its argument and -1.

The unary "plus" (+) operator returns the value of its single argument, effectively returning as its value the product of its argument and +1.

Level 2 — Exponentiation (** or ^)

The value of the left argument is raised to the power indicated by the right argument. Non-integer powers are allowed. The ^ and ** operators are both supported to provide compatibility with programs written for other COBOL implementations.

Level 3 — Multiplication (*) and division (/)

The * operator computes the product of the left and right arguments while the / operator computes the value of the left argument divided by the value of the right argument. If the right argument has a value of zero, expression evaluation will be prematurely terminated before a value is generated. This may cause program failure at run-time.

A sequence of multiple 3rd-level operations ($\mathbb{A} * \mathbb{B} / \mathbb{C}$, for example) will evaluate in strict left-to-right sequence if no parenthesis are used to control the order of evaluation.

Level 4 — Addition (+) or subtraction (+)

The + operator calculates the sum of the left and right arguments while the - operator computes the value of the right argument subtracted from that of the left argument.

A sequence of multiple 4th-level operations (A - B + C, for example) will evaluate in strict left-to-right sequence if no parenthesis are used to control the order of evaluation

The syntactical rules of COBOL, allowing a dash (-) character in data item names, can lead to some ambiguity.

```
01 C PIC 9 VALUE 5.
01 D PIC 9 VALUE 2.
01 C-D PIC 9 VALUE 7.
01 I PIC 9 VALUE 0.
...
COMPUTE I=C-D+1
```

The COMPUTE (see [COMPUTE], page 260) statement will evaluate the arithmetic expression C-D+1 and then save that result in I.

What value will be stored in I? The number 4, which is the result of subtracting the value of D (2) from the value of C (5) and then adding 1? Or, will it be the number 8, which is the value of adding 1 to the value of data item C-D (7)?

The right answer is 8 — the value of data item C-D plus 1! Hopefully, that was the intended result.

The GnuCOBOL compiler actually went through the following decision-making logic when generating code for the COMPUTE Statement:

- 1. Is there a data item named C-D defined? If so, use its value for the character sequence C-D.
- 2. If there is no C-D data item, then are there C and D data items? If not, the COMPUTE statement is in error. If there are, however, then code will be generated to subtract the value of D from C and add 1 to the result.

Had there been at least one space to the left and/or the right of the -, there would have been no ambiguity — the compiler would have been forced to use the individual C and D data items.

To avoid any possible ambiguity, as well as to improve program readability, it's considered good COBOL programming practice to always code at least one space to both the left and right of every operator in arithmetic expressions as well as the = sign on a COMPUTE.

Here are some examples of how the precedence of operations affects the results of arithmetic expressions (all examples use numeric literals, to simplify the discussion).

Expression	Result	Notes
3 * 4 + 1	13	* has precedence over +
4 * 2 ^ 3 - 10	22	2^3 is 8 ($^$ has precedence over *), times 4 is 32, minus 10 is 22.

(4 * 2) ^ 3 - 10	502	Parenthesis provide for a recursive application of the arithmetic expression rules, effectively allowing you to alter the precedence of operations. 4 times 2 is 8 (the use of parenthesis "trumps" the exponentiation operator, so the multiplication happens first); 8 ^ 3 is 512 minus 10 is 502.		
5 / 2.5 + 7 * 2 - 1.15	15.35	Integer and non-integer operands may be freely intermixed		

Of course, arithmetic expression operands may be numeric data items (any USAGE except POINTER or PROGRAM POINTER) as well as numeric literals.

2.2.5. Conditional Expressions

Conditional expressions are expressions which identify the circumstances under which a program may take an action or cease taking an action. As such, conditional expressions produce a value of TRUE or FALSE.

There are seven types of conditional expressions, as discussed in the following sections.

2.2.5.1. Condition Names

These are the simplest of all conditions. Observe the following code:

05	SHIRT-SIZE	PIC 99V9.	
	88 TINY	VALUE 0 THRU 12.5	
	88 XS	VALUE 13 THRU 13.5.	
	88 S	VALUE 14, 14.5.	
	88 M	VALUE 15, 15.5.	
	88 L	VALUE 16, 16.5.	
	88 XL	VALUE 17, 17.5.	
	88 XXL	VALUE 18, 18.5.	
	88 XXXL	VALUE 19, 19.5.	
	88 VERY-LARGE	VALUE 20 THRU 99.9.	

The condition names TINY, XS, S, M, L, XL, XXXL and VERY-LARGE will have TRUE or FALSE values based upon the values within their parent data item (SHIRT-SIZE).

A program wanting to test whether or not the current SHIRT-SIZE value can be classified as XL could have that decision coded as a combined condition (the most complex type of conditional expression), as either:

```
IF SHIRT-SIZE = 17 OR SHIRT-SIZE = 17.5
- or -
IF SHIRT-SIZE = 17 OR 17.5
Or it could simply utilize the condition name XL as follows:
IF XL
```

2.2.5.2. Class Conditions

Class conditions evaluate the type of data that is currently stored in a data item.

- 1. The NUMERIC class test considers only the characters '0', '1', ..., '9' to be numeric; only a data item containing nothing but digits will pass a NUMERIC class test. Spaces, decimal points, commas, currency signs, plus signs, minus signs and any other characters except the digit characters will all fail NUMERIC class tests.
- 2. The ALPHABETIC class test considers only upper-case letters, lower-case letters and spaces to be alphabetic in nature.
- 3. The ALPHABETIC-LOWER and ALPHABETIC-UPPER class conditions consider only spaces and the respective type of letters to be acceptable in order to pass such a class test.
- 4. The NOT option reverses the TRUE/FALSE value of the condition.
- 5. Note that what constitutes a "letter" (or upper/lower case too, for that manner) may be influenced through the use of CHARACTER CLASSIFICATION specifications in the OBJECT-COMPUTER (see [OBJECT-COMPUTER], page 82) paragraph.
- 6. Only data items whose USAGE (see [USAGE], page 198) is either explicitly or implicitly defined as DISPLAY may be used in NUMERIC or any of the ALPHABETIC class conditions.
- 7. Some COBOL implementations disallow the use of group items or PIC A items with NUMERIC class conditions and the use of PIC 9 items with ALPHABETIC class conditions. GnuCOBOL has no such restrictions.
- 8. The OMITTED class condition is used when it is necessary for a subprogram to determine whether or not a particular argument was passed to it. In such class conditions, *identifier-1* must be a linkage section item defined on the USING clause of the subprograms PROCEDURE DIVISION header. See [PROCEDURE DIVISION USING], page 212, for additional information.

The class-name-1 option allows you to test for a user-defined class. Here's an example. First, assume the following SPECIAL-NAMES (see [SPECIAL-NAMES], page 84) definition of the user-defined class 'Hexadecimal':

```
SPECIAL-NAMES.
```

```
CLASS Hexadecimal IS '0' THRU '9', 'A' THRU 'F', 'a' THRU 'f'.
```

Now observe the following code, which will execute the 150-Process-Hex-Value procedure if Entered-Value contains nothing but valid hexadecimal digits:

IF Entered-Value IS Hexadecimal

 $\begin{array}{cccc} {\tt PERFORM} & {\tt 150-Process-Hex-Value} \\ {\tt END-IF} & \end{array}$

2.2.5.3. Sign Conditions

Sign conditions evaluate the numeric state of a data item defined with a PICTURE (see [PICTURE], page 176) and/or USAGE (see [USAGE], page 198) that supports numeric values.

- 1. A POSITIVE or NEGATIVE class condition will be TRUE only if the value of identifier-1 is strictly greater than or less than zero, respectively.
- 2. A ZERO class condition can be passed only if the value of identifier-1 is exactly zero.
- 3. The NOT option reverses the TRUE/FALSE value of the condition.

2.2.5.4. Switch-Status Conditions

In the SPECIAL-NAMES paragraph, an external switch name can be associated with one or more condition names. These condition names may then be used to test the ON/OFF status of the external switch.

Here are the relevant sections of code in a program named testprog, which is designed to simply announce if SWITCH-1 is on:

```
ENVIRONMENT DIVISION.

SPECIAL-NAMES.

SWITCH-1 ON STATUS IS Switch-1-Is-ON.

...

PROCEDURE DIVISION.

...

IF Switch-1-Is-ON

DISPLAY "Switch 1 Is On"

END-IF
```

The following are two different command window sessions — the left on a Unix/Cygwin/OSX system and the right on a windows system — that will set the switch on and then execute the testprog program. Notice how the message indicating that the program detected the switch was set is displayed in both examples:

{ >=

{ <=

2.2.5.5. Relation Conditions

```
Relation-Condition Syntax
                                                                              }
{ identifier-1
                            } IS [ NOT ] RelOp { identifier-2
{ literal-1
                            }
                                                 { literal-2
                                                                              }
{ arithmetic-expression-1 }
                                                 { arithmetic-expression-2 }
                            }
{ index-name-1
                                                 { index-name-2
                                                                              }
                                     RelOp Syntax
                             }
{ EQUAL TO
{ ~~~~
                             }
                             }
{ EQUALS
                             }
{ GREATER THAN
{ GREATER THAN OR EQUAL TO }
{
                             }
{ LESS THAN
                             }
{ LESS THAN OR EQUAL TO
                             }
{ =
                             }
{ >
                             }
```

These conditions evaluate how two different values "relate" to each other.

}

}

}

- 1. When comparing one numeric value to another, the USAGE (see [USAGE], page 198) and number of significant digits in either value are irrelevant as the comparison is performed using the actual algebraic values.
- 2. When comparing strings, the comparison is made based upon the program's collating sequence. When the two string arguments are of unequal length, the shorter is assumed to be padded (on the right) with a sufficient number of spaces as to make the two strings of equal length. String comparisons take place on a corresponding character-by-character basis, left to right, until the TRUE/FALSE value for the relation test can be established. Characters are compared according to their relative position in the program's COLLATING SEQUENCE (as defined in SPECIAL-NAMES (see [SPECIAL-NAMES], page 84)), not according to the bit-pattern values the characters have in storage.
- 3. By default, the program's COLLATING SEQUENCE will, however, be based entirely on the bit-pattern values of the various characters.
- 4. There is no functional difference between using the wordy version (IS EQUAL TO, IS LESS THAN, ...) versus the symbolic version (=, <, ...) of the actual relation operators.

2.2.5.6. Combined Conditions

Combined Condition Syntax [(] Condition-1 [)] { AND } [(] Condition-2 [)] { ~~~ } { OR } { ~~~ }

A combined condition is one that computes a TRUE/FALSE value from the TRUE/FALSE values of two other conditions (which could themselves be combined conditions).

- 1. If either condition has a value of TRUE, the result of ORing the two together will result in a value of TRUE. ORing two FALSE conditions will result in a value of FALSE.
- 2. In order for AND to yield a value of TRUE, both conditions must have a value of TRUE. In all other circumstances, AND produces a FALSE value.
- 3. When chaining multiple, similar conditions together with the same operator (OR/AND), and left or right arguments have common subjects, it is possible to abbreviate the program code. For example:

```
 \mbox{ IF ACCOUNT-STATUS = 1 OR ACCOUNT-STATUS = 2 OR ACCOUNT-STATUS = 7 }  \mbox{ Could be abbreviated as:}
```

```
IF ACCOUNT-STATUS = 1 OR 2 OR 7
```

4. Just as multiplication takes precedence over addition in arithmetic expressions, so does AND take precedence over OR in combined conditions. Use parenthesis to change this precedence, if necessary. For example:

```
FALSE AND FALSE OR TRUE AND TRUE
```

Evaluates to TRUE

(FALSE AND FALSE) OR (TRUE AND TRUE)

Evaluates to TRUE (since AND has precedence over OR) - this is identical to the previous example

```
(FALSE AND (FALSE OR TRUE)) AND TRUE
Evaluates to FALSE
```

2.2.5.7. Negated Conditions

Negated Condition Syntax

NOT Condition-1

A condition may be negated by prefixing it with the NOT operator.

- 1. The NOT operator has the highest precedence of all logical operators, just as a unary minus sign (which "negates" a numeric value) is the highest precedence arithmetic operator.
- 2. Parenthesis must be used to explicitly signify the sequence in which conditions are evaluated and processed if the default precedence isn't desired. For example:

NOT TRUE AND FALSE AND NOT FALSE

Evaluates to FALSE AND TRUE which evaluates to FALSE

NOT (TRUE AND FALSE AND NOT FALSE)

Evaluates to NOT (FALSE) which evaluates to TRUE

NOT TRUE AND (FALSE AND NOT FALSE)

Evaluates to FALSE AND (FALSE AND TRUE) which evaluates to FALSE

2.2.6. Use of Periods

All COBOL implementations distinguish between sentences and statements in the procedure division. A *Statement* is a single executable COBOL instruction. For example, these are all statements:

```
MOVE SPACES TO Employee-Address
ADD 1 TO Record-Counter
DISPLAY "Record-Counter=" Record-Counter
```

Some COBOL statements have a *scope of applicability* associated with them where one or more other statements can be considered to be part of or related to the statement in question. An example of such a situation might be the following, where the interest on a loan is being calculated and displayed at 4% interest if the loan balance is under \$10,000, and 4.5% otherwise. (WARNING: the following code has an error!):

```
IF Loan-Balance < 10000
    MULTIPLY Loan-Balance BY 0.04 GIVING Interest
ELSE
    MULTIPLY Loan-Balance BY 0.045 GIVING Interest
DISPLAY "Interest Amount = " Interest</pre>
```

In this example, the IF statement actually has a scope that can include two sets of associated statements: one set to be executed when the IF (see [IF], page 291) condition is TRUE, and another if it is FALSE.

Unfortunately, there's a problem with the above. A human being looking at that code would probably infer that the DISPLAY (see [DISPLAY], page 263) statement, because of its lack of indentation, is to be executed regardless of the TRUE/FALSE value of the IF condition. Unfortunately, the compiler (any COBOL compiler) won't see it that way because it really couldn't care less what sort of indentation, if any, is used. In fact, any COBOL compiler would be just as happy to see the code written like this:

```
IF Loan-Balance < 10000 MULTIPLY Loan-balance
BY 0.04 GIVING Interest ELSE MULTIPLY
Loan-Balance BY 0.045 GIVING Interest DISPLAY
"Interest Amount = " Interest
```

How then do we inform the compiler that the DISPLAY statement is outside the scope of the IF?

That's where sentences come in.

A COBOL Sentence is defined as any arbitrarily long sequence of statements, followed by a period (.) character. The period character is what terminates the scope of a set of statements. Therefore, our example should have been coded like this:

```
IF Loan-Balance < 10000
    MULTIPLY Loan-Balance BY 0.04 GIVING Interest
ELSE
    MULTIPLY Loan-Balance BY 0.045 GIVING Interest.
DISPLAY "Interest Amount = " Interest</pre>
```

See the period at the end of the second MULTIPLY (see [MULTIPLY], page 307)? That is what terminates the scope of the IF, thus making the DISPLAY statement's execution completely independent of the TRUE/FALSE status of the IF.

2.2.7. Use of VERB/END-VERB Constructs

Prior to the 1985 COBOL standard, using a period character was the only way to signal the end of a statement's scope.

Unfortunately, this caused some problems. Take a look at this code:

```
IF A = 1
    IF B = 1
        DISPLAY "A & B = 1"

ELSE *> This ELSE has a problem!
    IF B = 1
        DISPLAY "A NOT = 1 BUT B = 1"
    ELSE
        DISPLAY "NEITHER A NOR B = 1".
```

The problem with this code is that indentation — so critical to improving the human-readability of a program — can provide an erroneous view of the logical flow. An ELSE is always associated with the most-recently encountered IF; this means the emphasized ELSE will be associated with the IF B = 1 statement, not the IF A = 1 statement as the indentation would appear to imply.

This sort of problem led to a band-aid solution being added to the COBOL language: the NEXT SENTENCE clause:

```
IF A = 1
    IF B = 1
        DISPLAY "A & B = 1"
    ELSE
        NEXT SENTENCE

ELSE
    IF B = 1
        DISPLAY "A NOT = 1 BUT B = 1"
    ELSE
        DISPLAY "NEITHER A NOR B = 1".
```

NEXT SENTENCE informs the compiler that if the B=1 condition is false, control should fall into the first statement that follows the next period.

With the 1985 standard for COBOL, a much more elegant solution was introduced. Any COBOL *Verb* (the first reserved word of a statement) that needed such a thing was allowed to use an END-*verb* construct to end its scope without disrupting the scope of any other statement it might have been in. Any COBOL 85 compiler would have allowed the following solution to our problem:

```
IF A = 1
    IF B = 1
        DISPLAY "A & B = 1"
    END-IF

ELSE
    IF B = 1
        DISPLAY "A NOT = 1 BUT B = 1"
    ELSE
        DISPLAY "NEITHER A NOR B = 1".
```

This new facility made the period almost obsolete, as our program segment would probably be coded like this today:

```
IF A = 1
```

```
IF B = 1
DISPLAY "A & B = 1"
END-IF

ELSE
IF B = 1
DISPLAY "A NOT = 1 BUT B = 1"
ELSE
DISPLAY "NEITHER A NOR B = 1"
END-IF

END-IF
```

COBOL (GnuCOBOL included) still requires that each procedure division paragraph contain at least one sentence if there is any executable code in that paragraph, but a popular coding style is now to simply code a single period right before the end of each paragraph.

The standard for the COBOL language shows the various END-verb clauses are optional because using a period as a scope-terminator remains legal.

If you will be porting existing code over to GnuCOBOL, you'll find it an accommodating facility capable of conforming to whatever language and coding standards that code is likely to use. If you are creating new GnuCOBOL programs, however, I would strongly counsel you to use the END-verb structures in those programs.

2.2.8. Concurrent Access to Files

The manipulation of data files is one of the COBOL language's great strengths. There are features built into COBOL to deal with the possibility that multiple programs may be attempting to access the same file concurrently. Multiple program concurrent access is dealt with in two ways — file sharing and record locking.

Not all GnuCOBOL implementations support file sharing and record-locking options. Whether they do or not depends upon the operating system they were built for and the build options that were used when the specific GnuCOBOL implementation was generated.

2.2.8.1. File Sharing

GnuCOBOL controls concurrent-file access at the highest level through the concept of file sharing, enforced when a program attempts to open a file. This is accomplished via a UNIX operating-system routine called fcntl. That module is not currently supported by Windows and is not present in the MinGW Unix-emulation package. GnuCOBOL builds created using a MinGW environment will be incapable of supporting file-sharing controls — files will always be shared in such environments. A GnuCOBOL build created using the Cygwin environment on Windows would have access to fcntl and therefore will support file sharing. Of course, actual Unix builds of GnuCOBOL, as well as OSX builds, should have no issues because fcntl should be available.

Any limitations imposed on a successful OPEN (see [OPEN], page 309) will remain in place until your program either issues a CLOSE (see [CLOSE], page 258) against the file or the program terminates.

File sharing is controlled through the use of a SHARING clause:

This clause may be used either in the file's SELECT statement (see [SELECT], page 95), on the OPEN statement (see [OPEN], page 309) which initiates your program's use of the file, or both. If a SHARING option is specified in *both* places, the specifications made on the OPEN statement will take precedence over those from the SELECT statement.

Here are the meanings of the three options:

- ALL OTHER When your program opens a file with this sharing option in effect, no restrictions will be placed on other programs attempting to OPEN the file after your program did. This is the default sharing mode.
- NO OTHER When your program opens a file with this sharing option in effect, your program announces that it is unwilling to allow any other program to have any access to the file as long as you are using that file; OPEN attempts made in other programs will fail with a file status of 37 (PERMISSION DENIED) until such time as you CLOSE (see [CLOSE], page 258) the file.
- READ ONLY Opening a file with this sharing option indicates you are willing to allow other programs to OPEN the file for input while you have it open. If they attempt any other OPEN, theirs will fail with a file status of 37. Of course, your program may fail if someone else got to the file first and opened it with a sharing option that imposed file-sharing limitations.

If the SELECT of a file is coded with a FILE STATUS clause, OPEN failures — including those induced by sharing failures — will be detectable by the program and a graceful recovery (or at least a graceful termination) will be possible. If no such clause was coded, however, a runtime message will be issued and the program will be terminated.

2.2.8.2. Record Locking

Record-locking is supported by advanced file-management software built-in to the GnuCOBOL implementation you are using. This software provides a single point-of-control for access to files — usually ORGANIZATION INDEXED files. One such runtime package capable of doing this is the Berkeley Database (BDB) package — a package frequently used in GnuCOBOL builds to support indexed files.

The various I/O statements your program can execute are capable of imposing limitations on access by other concurrently-executing programs to the file record they just accessed. These limitations are syntactically imposed by placing a lock on the record using a LOCK clause. Other records in the file remain available, assuming that file-sharing limitations imposed at the time the file was opened didn't prevent access to the entire file.

- 1. If the GnuCOBOL build you are using was configured to use the Berkeley Database (BDB) package for indexed file I/O, record locking will be available by using the DB_HOME run-time environment variable.
- 2. If the SELECT (see [SELECT], page 95) statement or file OPEN (see [OPEN], page 309) specifies SHARING WITH NO OTHER, record locking will be disabled.
- 3. If the file's SELECT contains a LOCK MODE IS AUTOMATIC clause, every time a record is read from the file, that record is automatically locked. Other programs may access *other* records within the file, but not a locked record.
- 4. If the file's SELECT contains a LOCK MODE IS MANUAL clause, locks are placed on records *only* when a READ statement executed against the file includes a LOCK clause (this clause will be discussed shortly).
- 5. If the LOCK ON clause is specified in the file's SELECT, locks (either automatically or manually acquired) will continue to accumulate as more and more records are read, until they are explicitly released. This is referred to as multiple record locking.

Locks acquired via multiple record locking remain in effect until the program holding the lock...

- ...terminates, or ...
- ...executes a CLOSE statement (see [CLOSE], page 258) against the file, or ...
- ...executes an UNLOCK statement (see [UNLOCK], page 355) against the file, or ...
- ...executes a COMMIT statement (see [COMMIT], page 259) or ...
- ... executes a ROLLBACK statement (see [ROLLBACK], page 326).
- 6. If the LOCK ON clause is *not* specified, then the next I/O statement your program executes, except for START (see [START], page 343), will release the lock. This is referred to as *single record locking*.
- 7. A LOCK clause, which may be coded on a READ (see [READ], page 316), REWRITE (see [REWRITE], page 324) or WRITE statement (see [WRITE], page 360) looks like this:

The WITH [NO] LOCK option is the only one available to REWRITE or WRITE statements.

The meanings of the various record locking options are as follows:

IGNORING LOCK

WITH IGNORE LOCK

These options (which are synonymous) inform GnuCOBOL that any locks held by other programs should be ignored.

WITH LOCK Access to the record by other programs will be denied.

WITH NO LOCK

The record will not be locked. This is the default for all statements.

WITH KEPT LOCK

When single record locking is in effect, as a new record is accessed, locks held for previous records are released. By using this option, not only is the newly accessed record locked (as WITH LOCK would do), but prior record locks will be retained as well. A subsequent READ without the KEPT LOCK option will release all "kept" locks, as will the UNLOCK statement.

WITH WAIT This option informs GnuCOBOL that the program is willing to wait for a lock held (by another program) on the record being read to be released.

Without this option, an attempt to read a locked record will be immediately aborted and a file status of 51 will be returned.

With this option, the program will wait for a preconfigured time for the lock to be released. If the lock is released within the preconfigured wait time, the read will be successful. If the preconfigured wait time expires before the lock is released, the read attempt will be aborted and a 51 file status will be issued.

End of Chapter 2 — COBOL Fundamentals

3. CDF - Compiler Directing Facility

The Compiler Directing Facility, or CDF, is a means of controlling the compilation of Gnu-COBOL programs. CDF provides a mechanism for dynamically setting or resetting certain compiler switches, introducing new source code from one or more source code libraries, making dynamic source code modifications and conditionally processing or ignoring source statements altogether. This is accomplished via a series of special CDF statements and directives that will appear in the program source code.

When the compiler is operating in Fixed Format Mode, all CDF statements must begin in column eight (8) or beyond.

There are two types of supported CDF statements in GnuCOBOL — Text Manipulation Statements and Compiler Directives.

The CDF text manipulation statements COPY and REPLACE are used to introduce new code into programs either with or without changes, or may be used to modify existing statements already in the program. Text manipulation statements are always terminated with a period.

CDF directives, denoted by the presence of a >> character sequence as part of the statement name itself, influence the process of program compilation.

Compiler directives are *never* terminated with a period.

The compiler command-line option -D offers additional control (see [cobc - The GnuCOBOL Compiler], page 559).

3.1. >> CALL-CONVENTION

>>CALL-CONVENTION { COBOL } **EXTERN } { STDCALL } { STATIC }

This directive instructs the compiler how to treat references to program names and may be used to determine other details for interacting with a function or program. There are four options with COBOL being the default.

COBOL The program name is treated as a COBOL word that maps to the externalised name program to be called, cancelled or referenced in the program-address-identifier, applying the same mapping rules as for a program name for which no AS phrase is specified. (The is the default.)

EXTERN The program name is treated as an external reference.

STDCALL [more info needed]

STATIC The program name is called as a included element and not dynamically which is the

normal default.

3.2. COPY

CDF COPY Statement Syntax

```
COPY copybook-name

"""

[ IN|OF library-name ]

"" ""

[ SUPPRESS PRINTING ]

"""

[ REPLACING { Phrase-Clause | String-Clause }... ] ...
```

CDF COPY Phrase-Clause Syntax

CDF COPY String-Clause Syntax

```
~~~~~~ ~~~~~
```

[LEADING|TRAILING] ==partial-word-1== BY ==partial-word-2==

- 1. COPY statements are used to import copybooks (see [Copybooks], page 13) into a program.
- 2. COPY statements may be used anywhere within a COBOL program where the code contained within the copybook would be syntactically valid.
- 3. The optional SUPPRESS clause (with or without the optional PRINTING reserved word) is valid syntactically but is non-functional. It is supported to facilitate compatibility with source code written for other versions of COBOL.
- 4. There is no difference between the use of the word IN and the word OF use the one you prefer.
- 5. A period is absolutely mandatory at the end of every COPY statement, even if the statement occurs within the scope of another one where a period might appear disruptive, such as within the scope of an IF (see [IF], page 291) statement. This mandatory period at the end of the statement does not, however, affect the statement scope in which the COPY occurs.
- 6. Both pseudo-text-2 and partial-word-2 may be null.
- 7. All COPY statements are located and the contents of the corresponding copybooks inserted into the program source code before the actual compilation process begins. If a copybook contains a COPY statement, the copybook insertion process will be repeated to resolve the embedded COPY. This will continue until no unresolved COPY statements remain. At that point, actual program compilation will begin.

- 8. See [Locating Copybooks], page 574, for the specific rules on how copybooks are located by the compiler.
- 9. The optional REPLACING clause allows for one or more of either of the following kinds of text replacements to be made:

Phrase-Clause

Replacement of one or more complete reserved words, user-defined identifiers or literals; the following points apply to this option:

- This option cannot be used to replace part of a word, identifier or literal.
- Whatever precedes the BY will be referred to here as the search string.
- Single-item search strings can be specified by coding the *identifier-1*, *literal-1* or *word-1* being replaced.
- Multiple-item search strings can be specified using the ==pseudo-text-1== option. For example, to replace all occurrences of UPON PRINTER, you would specify ==UPON PRINTER==.
- The replacement string, which follows the BY, may be specified using any of the four options.
- If the replacement string is a multiple-item phrase or is to be deleted altogether, you must use the ==pseudo-text-2== option. If pseudo-text-2 is null (in other words, the replacement text is specified as ====), all encountered occurrences of the search string will be deleted.

String-Clause

Using this, you may replace character sequences that occur at the beginning (see LEADING) or end (see TRAILING) of reserved or user-defined words. For example, to change all words of the form "0100-xxxxxx" to "020-xxxxxx", code LEADING ==0100-== BY ==020-==. To simply remove all "0100-" prefixes from words, code LEADING ==0100-== BY =====.

3.3. REPLACE

CDF REPLACE Statement (Format 1) Syntax REPLACE [ALSO] { Phrase-Clause | String-Clause }... .

CDF REPLACE Statement (Format 2) Syntax

```
REPLACE [ LAST ] OFF
```

CDF REPLACE Phrase-Clause Syntax

```
{ ==pseudo-text-1== } BY { ==pseudo-text-2== }
```

CDF REPLACE String-Clause Syntax

```
[ LEADING|TRAILING ] ==partial-word-1== BY ==partial-word-2==
```

- 1. The REPLACE statement provides a mechanism for changing all or part of one or more ${\it GnuCOBOL}$ statements.
- 2. A period is absolutely mandatory at the end of every REPLACE statement (either format), even if the statement occurs within the scope of another one where a period might appear disruptive (such as within the scope of an IF (see [IF], page 291) statement; the period will not, however, affect the statement scope in which the REPLACE occurs.
- 3. The following points apply to Format 1 of the REPLACE statement:
 - A. Format 1 of the REPLACE statement can be used to make changes to program source code in much the same way as the REPLACING option of the COPY statement can, via these options:

Phrase-Clause

Replace one or more complete reserved words, user-defined identifiers or literals; the following points apply to this option:

- This option cannot be used to replace part of a word, identifier or literal.
- Whatever precedes the BY will be referred to here as the search string.
- Search strings on REPLACE are always specified using the ==pseudotext-1== option. For example, to replace all occurrences of UPON PRINTER, you would specify ==UPON PRINTER==.

• The replacement string, which follows the BY, is specified using the ==pseudo-text-2== option. If pseudo-text-2 is null (in other words, the replacement text is specified as ====), all encountered occurrences of the search string will be deleted.

String-Clause

Using this, you may replace character sequences that occur at the beginning (see LEADING) or end (see TRAILING) of reserved or user-defined words. For example, to change all words of the form "0100-xxxxxx" to "020-xxxxxx", code LEADING ==0100-== BY ==020-==. To simply remove all "0100-" prefixes from words, code LEADING ==0100-== BY =====.

- B. Once a Format 1 REPLACE statement is encountered in the currently-compiling source file, Replace Mode becomes active, and the change(s) specified by that statement will be automatically made on all subsequent source statements the compiler reads from the file.
- C. Replace Mode remains in-effect continuing to make source code changes until another Format 1 REPLACE is encountered, the end of currently compiling program source file is reached or a Format 2 REPLACE statement is encountered.
- D. When a Format 1 REPLACE statement with the ALSO keyword is encountered without Replace Mode being currently active, the effect will be as if the ALSO had not been specified. If Replace Mode already was in effect, the effect will be to "push" the current change specification(s) onto the top of a stack and add the specification(s) of the new statement to those that were already in effect.
- E. When a Format 1 REPLACE without the ALSO keyword is encountered, any stacked change specification(s), if any, will be discarded and the currently in-effect change specification(s), if any, will be replaced by those of the new statement.
- F. When the end of the currently-compiling source file is reached, Replace Mode is deactivated and any stacked replace specifications will be discarded compilation of the next source file (if any) will begin with Replace Mode inactive and no change specification(s) on the stack.
- 4. The following points apply to Format 2 of the REPLACE statement:
 - A. If Replace Mode is currently inactive, the Format 2 REPLACE statement will be ignored.
 - B. If Replace Mode is currently active, a REPLACE OFF. will deactivate Replace Mode and discard any replace specification(s) on the stack. The compiler will henceforth operate as if no REPLACE had ever been encountered, until such time as another Format 1 REPLACE is encountered.
 - C. If Replace Mode is currently active, a REPLACE LAST OFF. will replace the current replace specification(s) with those popped off the top of the stack. If there were no replace specification(s) on the stack, the effect will be as if a REPLACE OFF. had been coded.

3.4. >>DEFINE

```
CDF >> DEFINE Directive Syntax

>> DEFINE [ CONSTANT ] cdf-variable-1 AS { OFF } { ~~~ } { ~~~~ } { literal-1 [ OVERRIDE ] } { ~~~~~~~~~~~ } { PARAMETER [ OVERRIDE ] }
```

Use the >>DEFINE CDF directive to create CDF variables and (optionally) assign them either literal or environment variable values.

- 1. The reserved word AS is optional and may be included, or not, at the discretion of the programmer. The presence or absence of this word has no effect upon the program.
- 2. CDF variables defined in this way become undefined once an END PROGRAM or END FUNCTION directive is encountered in the input source.
- 3. The >>DEFINE CDF directive is one way to create CDF variables that may be processed by other CDF statements such as >>IF (see [>>IF], page 64). The >>SET CDF directive (see [>>SET], page 66) provides another way to create them.
- 4. CDF variable names follow the rules for standard GnuCOBOL user-defined names, and may not duplicate any CDF reserved word. CDF variable names may duplicate COBOL reserved words, provided the CONSTANT option is not specified, but such names are not recommended.
- 5. The CONSTANT option is valid only in conjunction with *literal-1*. When CONSTANT is specified, the CDF variable that is created may be used within your regular COBOL code as if it were a literal value. Without this option, the CDF variable may only be referenced on other CDF statements. The OFF option is used to create a variable without assigning it any value.
- 6. The PARAMETER option is used to create a variable whose value is that of the environment variable of the same name. Note that this value assignment occurs at compilation time, not program execution time.
- 7. In the absence of the OVERRIDE option, cdf-variable-1 must not yet have been defined. When the OVERRIDE option is specified, cdf-variable-1 will be created with the specified value, if it had not yet been defined. If it had already been defined, it will be redefined with the new value.

3.5. >>IF

```
CDF >>IF Directive Syntax
>>IF CDF-Conditional-Expression-1
         [ Program-Source-Lines-1 ]
[ >>ELIF CDF-Conditional-Expression-2
  ~~~~~ [ Program-Source-Lines-2 ] ]...
[ >>ELSE
  ~~~~~ [ Program-Source-Lines-3 ] ]
>>END-IF
~~~~~~
                            CDF-Conditional-Expression Syntax
{ cdf-variable-1 } IS [ NOT ] { DEFINED
                                                                 }
{ literal-1
                                { ~~~~~
                                                                 }
                 }
                                                                 }
                                { SET
```

CDF-RelOp Syntax

{ CDF-RelOp { cdf-variable-2 } }

{ literal-2

{

{

```
>=
             GREATER THAN OR EQUAL TO
      or
                           ~~ ~~~~
            GREATER THAN
      or
<=
            LESS THAN OR EQUAL TO
      or
<
            LESS THAN
      or
            EQUAL TO
      or
<>
            EQUAL TO (with "NOT")
      or
```

The >>IF CDF directive causes the GnuCOBOL compiler to process or ignore COBOL source statements, CDF text-manipulation statements and CDF directives depending upon the value of one or more conditional expressions based upon CDF variables.

1. The reserved words IS, THAN and TO are optional and may be omitted. The presence or absence of these words has no effect on the program.

}

} }

- 2. Each >> IF directive must be terminated by an >> END-IF directive.
- 3. There may be any number of >>ELIF clauses following an >>IF, including zero.
- 4. There may no more than one >>ELSE clause following an >>IF. When >>ELSE is used, it must follow the >>IF and all >>ELIF clauses.
- 5. Only one of the *Program-Source-Lines-n* block of statements that lie within the scope of the >>IF ... >>END-IF may be processed by the compiler. Which one (if any) that gets processed will be decided as follows:
 - A. Each CDF-Conditional-Expression-n will be evaluated, in turn, in the sequence in which they are coded in the >>IF statement and any >>ELIF clauses that may be present until one evaluates to TRUE. Once one of them evaluates to TRUE, the Program-Source-Lines-n block of code that corresponds to the TRUE CDF-Conditional-Expression-n will be one that is processed. All others within the >>IF->>END-IF scope will be ignored.
 - B. If no CDF-Conditional-Expression evaluates to TRUE, and there is an >>ELSE clause, the Program-Source-Lines-3 block of statements following the >>ELSE clause will be processed by the compiler and all others within the >>IF->>END-IF scope will be ignored.
 - C. If no CDF-Conditional-Expression-n evaluates to TRUE and there is no >>ELSE clause, then none of the Program-Source-Lines-n block of statements within the >>IF->>END-IF scope will be processed by the compiler.
 - D. If the *Program-Source-Lines-n>* statement block selected for processing is empty, no error results there will just be no code generated from the <code>>>IF->>END-IF</code> structure.
- 6. A Program-Source-Lines-n block may contain any valid COBOL or CDF code.
- 7. The following points pertain to any CDF-Conditional-Expression-n:
 - A. The DEFINED option tests for whether *cdf-variable-1* has been defined, but not yet assigned a value (>>DEFINE ... OFF); use the NOT option to test for the variable not being defined.
 - B. The SET option tests for whether *cdf-variable-1* has been given a value, either via a >>SET statement or via a >>DEFINE without the OFF option.
 - C. Two CDF variables, two literals or a single CDF variable and a single literal may be compared against each other using a relational operator. Unlike the standard Gnu-COBOL IF statement (see [IF], page 291), multiple comparisons cannot be ANDed or ORed together; you may nest a second >>IF inside the first, however, to simulate an AND and an OR may be simulated via the >>ELIF option.
 - D. The <> symbol stands for NOT EQUAL TO.

3.6. >>SET

The >>SET CDF directive provides an alternate means of performing the actions of the >>DEFINE and >>SOURCE directives, as well as a means of controlling the compiler's -free switch, -fixed switch and -ffold-copy switch from within program source code.

- 1. The reserved word AS is optional (only on the SOURCEFORMAT and FOLDCOPYNAME clauses) and may be included, or not, at the discretion of the programmer. The presence or absence of this word has no effect upon the program.
- 2. CDF variables defined in this way become undefined once an END PROGRAM or END FUNCTION directive is encountered in the input source.
- 3. The FOLDCOPYNAME option provides the equivalent of specifying the compiler -ffold-copy=xxx switch, where xxx is either UPPER or LOWER.
- 4. The NOFOLDCOPYNAME option turns off the effect of either the >>SET FOLDCOPYNAME statement or the compiler -ffold-copy=xxx switch.
- 5. If the CONSTANT option is used, *literal-1* must also be used. This option provides another means of defining constants that may be used anywhere in the program that a literal could be specified.
- 6. The remaining options of the >>SET CDF directive provide equivalent functionality to the >>DEFINE and >>SOURCE directives, as follows:

3.7. >>SOURCE

CDF >>SOURCE Directive Syntax

>>SOURCE FORMAT IS FIXED|FREE|VARIABLE

The >>SOURCE CDF directive puts the compiler into FIXED or FREE source-code format mode. This, in effect, provides yet another mechanism for controlling the compiler's -free switch and -fixed switch.

- 1. The reserved words FORMAT and IS are optional and may be included, or not, at the discretion of the programmer. The presence or absence of these words has no effect upon the program.
- 2. You may switch between FIXED and FREE mode as desired.
- 3. You may also use the >>SET CDF directive to perform this function.
- 4. If the compiler is already in the specified mode, this statement will have no effect.

3.8. >>TURN

The directive will (de-)activate exception checks.

3.9. >>D

	CDF >>D Directive Syntax	
>>D		
~~~		

The directive removes all floating debug lines if debug mode not active. Otherwise will ignore the directive part of the line.

#### 3.10. >>DISPLAY

# CDF >>DISPLAY Directive Syntax >>DISPLAY source-text [ VCS = version-string ]

The directive is a v1.0 extension and will display messages during compilation.

#### 3.11. >>PAGE

# CDF >>PAGE Directive Syntax >>PAGE [ comment-text ]

The PAGE directive specifies page ejection and provides documentation for the source listing.

- 1. Comment-Text may contain any character in the computers standard character coded set except for control characters.
- 2. Comment-Text is not checked for syntax and only serves as documentation.
- 3. if a source listing is being produced a PAGE directive shall cause page ejection followed by listing of the PAGE directive.
- 4. If a listing is not being produced the directive will have no effect.

### 3.12. >>LISTING

		CDF >>LISTING Directive Syntax	
>>LISTING	{ON} {OFF}		

The directive allows the program listing to be de-(activated).

#### 3.13. >>LEAP-SECONDS

#### CDF >>LEAP-SECONDS Directive Syntax

>>LEAP-SECONDS

The >>LEAP-SECONDS CDF directive is syntactically recognized but is otherwise non-functional.

Allows for more than 60 seconds per minute.

#### 3.14. \$ Directives

# **CDF** \$ Directive Syntax \$ (Dollar) Directives - Active. These directives are active and have the same function as ones starting with >>: **\$DEFINE** \$DISPLAY ON|OFF \$IF \$ELIF \$ELSE \$ELSE-IF \$END \$SET It is recommended to use the standard directives only instead of the MF directives (when possible) as these have a higher chance for being portable. \$ (Dollar) Directives - Not Active. These are NOT active and will produce a warning message: \$DISPLAY VCS ... Recognised but otherwise ignored. **@OPTIONS** options-text Additional Micro-Focus directives accepted : ADDRSV | ADD-RSV literal-1 ADDSYN | ADD-SYN literal-1 = literal-2 ASSIGN "EXTERNAL" | "DYNAMIC" BOUND CALLFH literal-1 COMP1 | COMP-1 "BINARY" | "FLOAT" FOLDCOPYNAME | FOLD-COPY-NAME AS "UPPER" | "LOWER"

NOFOLDCOPYNAME | NOFOLD-COPY-NAME | NO-FOLD-COPY-NAME

SOURCEFORMAT | SOURCE-FORMAT "FIXED" | "FREE" | "VARIABLE"

Offers support for MF Compiler Directives.

OVERRIDE literal-1 = literal-2

MAKESYN | MAKE-SYN NOBOUND | NO-BOUND

REMOVE literal-1

NOSSRANGE | NO-SSRANGE

SSRANGE "2"

#### 3.15. Predefined compilation variables

GnuCOBOL defines *compilation variables* when various conditions are true. If the condition associated with a variable is false, the variable is not defined.

DEBUG The -d debug flag is specified.

**EXECUTABLE** 

Module being compiled contains the main program.

GCCOMP

The size of a COMP *item* is determined according to the GnuCOBOL scheme where for a picture of length:

1 - 2 item = 1 byte

3 - 4 item = 2 bytes

5 - 9 item = 4 bytes

10 - 18 item = 8 bytes

GNUCOBOL GnuCOBOL is compiling the source unit.

HOSTSIGNS

A signed packed decimal item's value may be considered NUMERIC if sign = X"F".

**IBMCOMP** 

The size of a COMP *item* is determined according to the IBM scheme, where for a PICTURE of length:

1 - 4 item = 2 bytes

5 - 9 item = 4 bytes

10 - 18 item = 8 bytes

MODULE The element being compiled does not contain the main program.

NOHOSTSIGNS

A signed packed decimal item's value may not be considered NUMERIC if sign = X"F".

NOIBMCOMP

The size of a COMP item is *not* determined according to the IBM scheme.

NOSTICKY-LINKAGE

Sticky linkage (linkage section items remaining allocated between invocations) is *not* active.

NOTRUNC Numeric data items are truncated according to their internal representation.

P64 Pointers are greater than 32 bits.

STICKY-LINKAGE

Sticky linkage (linkage section items remaining allocated between invocations) is active.

TRUNC Numeric data items are truncated according to their PICTURE clauses.

While still supported, this may well be removed in the future and should not be used. See GCCOMP and GNUCOBOL instead:

OCCOMP The size of a COMP *item* is determined according to the GnuCOBOL scheme, where for a PICTURE of length:

1 - 2 item = 1 byte

3 - 4 item = 2 bytes

$$5 - 9$$
  $item = 4 bytes$   
 $10 - 18$   $item = 8 bytes$ 

OPENCOBOL

GnuCOBOL is compiling the source unit.

End of Chapter 3 — CDF - Compiler Directing Facility

#### 4. IDENTIFICATION DIVISION

#### **IDENTIFICATION DIVISION Syntax**

```
[{ IDENTIFICATION } DIVISION. ]
{ ~~~~~ } ~~~~~
{ ID
                }
{ PROGRAM-ID. } { program name } .
              } { literal-1      } [ AS { literal-2 } ] [ Type-clause ] .
{ FUNCTION-ID. } { literal-3 } [ AS literal-4 ] .
              { function-name } .
{ OPTIONS. }
[ DEFAULT ROUNDED MODE IS {AWAY-FROM-ZERO
                         {NEAREST-AWAY-FROM-ZERO }
                         {NEAREST-EVEN
                                                }
                         {NEAREST-TOWARDS-ZERO
                                                }
                         {PROHIBITED
                         {TOWARDS-GREATER
                                                }
                         {TOWARDS-LESSER
                                                }
                                                }]
                         {TRUNCATION
[ ENTRY-CONVENTION IS {COBOL
                              }
  ~~~~~~~~~~~~~~~
 {EXTERN }
 {STDCALL }]
[AUTHOR. comment-1.]
[DATE-COMPILED. comment-2.]
[DATE-MODIFIED. comment-3.
  ~~~~~~~~~~~~
[ DATE-WRITTEN. comment-4. ]
[ INSTALLATION. comment-5. ]
[ REMARKS.
                comment-6. ]
  ~~~~~
[SECURITY. comment-7.]
```

The AUTHOR, DATE-COMPILED, DATE-MODIFIED, DATE-WRITTEN, INSTALLATION, REMARKS and SECURITY paragraphs are supported by GnuCOBOL only to provide compatibility with programs written for the ANS1974 (or earlier) standards. As of the ANS1985 standard, these clauses have become obsolete and should not be used in new programs.

```
PROGRAM-ID Type Clause Syntax
```

```
IS [COMMON] [INITIAL|RECURSIVE PROGRAM]
```

The identification division provides basic identification of the program by giving it a name and optionally defining some high-level characteristics via the eight pre-defined paragraphs that may be specified.

- 1. The paragraphs shown above may be coded in any sequence.
- 2. The reserved words AS, IS and PROGRAM are optional and may be included, or not, at the discretion of the programmer. The presence or absence of these words has no effect upon the program.
- 3. A **Type Clause** may be coded only when PROGRAM-ID is specified. If one is coded, either COMMON, COMMON INITIAL or COMMON RECURSIVE must be specified.
- 4. While the actual IDENTIFICATION DIVISION or ID DIVISION header is optional, the PROGRAM-ID / FUNCTION-ID paragraphs are not; only one or the other, however, may be coded.
- 5. The compiler's -Wobsolete switch will cause the GnuCOBOL compiler to issue warnings messages if these (or any other obsolete syntax) is used in a program.
- 6. If specified, *literal-1* must be an actual alphanumeric literal and may not be a figurative constant.
- 7. The PROGRAM-ID and FUNCTION-ID paragraphs serve to identify the program to the external (i.e. operating system) environment. If there is no AS clause present, the *program-id* will serve as that external identification. If there is an AS clause specified, that specified literal will serve as the external identification. For the remainder of this document, that "external identification" will be referred to as the primary entry-point name.
- 8. The INITIAL, COMMON and RECURSIVE words are used only within subprograms serving as subroutines. Their purposes are as follows:
  - A. COMMON should be used only within subprograms that are nested subprograms. A nested subprogram declared as COMMON may be called from any nested program in the source file being compiled, not just those "above" it in the nesting structure.
  - B. The RECURSIVE clause, if any, will cause the compiler to generate different object code for the subprogram that will enable it to invoke itself and to properly return back to the program that invoked it.
    - User-defined functions (i.e. FUNCTION-ID) are always recursive.
  - C. The INITIAL clause, if specified, guarantees the subprogram will be in its initial (i.e. compiled) state each and every time it is executed, not just the first time.

End of Chapter 4 — IDENTIFICATION DIVISION

#### 5. ENVIRONMENT DIVISION

#### **ENVIRONMENT DIVISION Syntax**

```
ENVIRONMENT DIVISION.
[CONFIGURATION SECTION.]
[SOURCE-COMPUTER.
 Compilation-Computer-Specification .]
[OBJECT-COMPUTER.
 Execution-Computer-Specification .]
 ~~~~~~~~~~~~~~~~
[ SPECIAL-NAMES.
                         Program-Configuration-Specification . ]
[ REPOSITORY.
                         Function-Specification... ]
  ~~~~~~~~~~
[INPUT-OUTPUT SECTION.]
 [FILE-CONTROL.
 General-File-Description...]
 File-Buffering Specification... .]
[I-O-CONTROL.
```

This division defines the external computer environment in which the program will be operating. This includes defining any files that the program may be .

- If both optional sections of this division are coded, they must be coded in the sequence shown.
- The paragraphs within the sections may be coded in any order.
- These sections consist of a series of specific, pre-defined, paragraphs (SOURCE-COMPUTER and OBJECT-COMPUTER, for example), each of which serves a specific purpose. If no code is required for the purpose one of the paragraphs serves, the entire paragraph may be omitted.
- If any of the paragraphs within one of the sections are coded, the section header itself must be coded.
- If none of the paragraphs within one of the sections are coded, the section header itself may be omitted.
- If none of the sections within the environment division are coded, the ENVIRONMENT DIVISION. header itself may be omitted.

#### 5.1. CONFIGURATION SECTION

#### CONFIGURATION SECTION Syntax

This section defines the computer system upon which the program is being compiled and executed and also specifies any special environmental configuration or compatibility characteristics.

- 1. The four paragraphs in this section may be specified in any order but if not in this order, a warning will be issued.
- 2. The configuration section is not allowed in a nested subprogram. A nested program inherits the configuration section settings of its parent program.
- 3. If none of the features provided by the configuration section are required by a program, the entire CONFIGURATION SECTION. header may be omitted from the program.

#### 5.1.1. SOURCE-COMPUTER

# SOURCE-COMPUTER Syntax SOURCE-COMPUTER. computer-name [ WITH DEBUGGING MODE ] .

This paragraph defines the computer upon which the program is being compiled and provides one way in which debugging code embedded within the program may be activated.

- 1. The reserved word WITH is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. This paragraph is not allowed in a nested subprogram. A nested program inherits the SOURCE-COMPUTER settings of its parent program.
- 3. The value specified for *computer-name* is irrelevant, provided it is a valid COBOL word that does not match any GnuCOBOL reserved word. The *computer-name* value may include spaces. This need not match the *computer-name* used with the OBJECT-COMPUTER paragraph, if any.
- 4. The DEBUGGING MODE clause, if present, will inform the compiler that debugging lines (those with a 'D' in column 7 if Fixed Source Mode is in effect, or those prefixed with a >>D if Free Source Mode is in effect) normally treated as comments are to be compiled.
- 5. Even without the DEBUGGING MODE clause, it is still possible to compile debugging lines. Debugging lines may also be compiled by specifying the -fdebugging-line switch to the GnuCOBOL compiler.

#### 5.1.2. OBJECT-COMPUTER

#### **OBJECT-COMPUTER Syntax**

The MEMORY SIZE and SEGMENT-LIMIT clauses are syntactically recognized but are otherwise non-functional.

This paragraph describes the computer upon which the program will execute.

- 1. The *computer-name*, if specified, must immediately follow the OBJECT-COMPUTER paragraph name. The remaining clauses may be coded in any sequence.
- 2. The reserved words CHARACTER, IS, PROGRAM and SEQUENCE are optional and may be omitted. The presence or absence of these words has no effect on the program.
- 3. The value specified for *computer-name*, if any, is irrelevant provided it is a valid COBOL word that does not match any GnuCOBOL reserved word. The *computer-name* may include spaces. This need not match the *computer-name* used with the SOURCE-COMPUTER paragraph, if any.
- 4. The OBJECT-COMPUTER paragraph is not allowed in a nested subprogram. A nested program inherits the OBJECT-COMPUTER settings of its parent program.
- 5. The COLLATING SEQUENCE clause allows you to specify a customized character collating sequence to be used when alphanumeric values are compared to one another. Data will still be stored in the character set native to the computer, but the logical sequence in which characters are ordered for comparison purposes can be altered from that defined by the computer's native character set. The *alphabet-name-1* you specify needs to be defined in the SPECIAL-NAMES (see [SPECIAL-NAMES], page 84) paragraph.
- 6. If no COLLATING SEQUENCE clause is specified, the collating sequence implied by the character set native to the computer (usually ASCII) will be used.
- 7. The optional CLASSIFICATION clause may be used to specify a locale for the environment in which the program will execute, for the purpose of influencing the upper-case and lower-case mappings of characters for the UPPER-CASE (see [UPPER-CASE], page 459) and LOWER-CASE (see [LOWER-CASE], page 408) intrinsic functions and the classification of characters for the ALPHABETIC, ALPHABETIC-LOWER and ALPHABETIC-UPPER class tests. The definitions

of these classes is taken from the cultural convention specification (LC_CTYPE) from the specified locale.

The meanings of the four locale specifications are as follows:

- A. locale-name-1 references a LOCALE (see [SPECIAL-NAMES], page 84) definition.
- B. The keyword LOCALE refers to the current locale (in effect at the time the program is executed)
- C. The keyword USER-DEFAULT references the default locale specified for the user currently executing this program.
- D. The keyword SYSTEM-DEFAULT denotes the default locale specified for the computer upon which the program is executing.
- 8. Absence of a CLASSIFICATION clause will cause character classification to occur according to the rules for the computer's native character set (ASCII, EBCDIC, etc.).

#### 5.1.3. SPECIAL-NAMES

#### SPECIAL-NAMES Syntax

```
SPECIAL-NAMES.
 [CALL-CONVENTION integer-1 IS mnemonic-name-1]
 [CONSOLE IS CRT]
 [CRT STATUS IS identifier-1]
 [CURRENCY SIGN IS literal-1]
   ~~~~~~ ~~~
 [ CURSOR IS identifier-2 ]
 [ DECIMAL-POINT IS COMMA ]
   . . . . . . . . . . . . . . .
 [ EVENT STATUS IS identifier-3 ]
 [ LOCALE locale-name-1 IS literal-2 ]...
 [ NUMERIC SIGN IS TRAILING SEPARATE ]
   ~~~~~~~ ~~~~~~
 [SCREEN CONTROL IS identifier-4]
 [device-name-1 IS mnemonic-name-2]...
 [feature-name-1 IS mnemonic-name-3]...
 [Alphabet-Clause]...
 [Class-Definition-Clause]...
 [Switch-Definition-Clause]...
 [Symbolic-Characters-Clause]...
```

The EVENT STATUS and SCREEN CONTROL clauses are syntactically recognized but are otherwise non-functional.

Alphabet-Name-Clause, Class-Definition-Clause, Switch-Definition-Clause and Symbolic-Characters-Clause are discussed in detail in the next four sections.

The SPECIAL-NAMES paragraph provides a means for specifying various program and operating environment configuration options.

1. The various clauses that may be specified within the SPECIAL-NAMES paragraph may be coded in any order.

- 2. The reserved word IS is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 3. The SPECIAL-NAMES paragraph is not allowed in a nested subprogram. A nested program inherits the SPECIAL-NAMES settings of its parent program.
- 4. Only the final clause specified within this paragraph should be terminated with a period.
- 5. The CALL-CONVENTION clause allows a decimal integer, representing a series of ON/OFF switch settings, to be associated with a mnemonic name which may then be coded on a CALL statement (see [CALL], page 253). The switch settings defined by this mnemonic will then control how the linkage to a subroutine invoked by the CALL statement that references mnemonic-name-1 will be handled.
- 6. The CONSOLE IS CRT clause, if specified, will cause a DISPLAY statement lacking an explicit UPON clause to be treated as a DISPLAY data-item statement (see [DISPLAY data-item], page 268), and any ACCEPT statement lacking a FROM clause to be treated as a ACCEPT data-item statement (see [ACCEPT data-item], page 234).
- 7. If the CRT STATUS clause is not specified, an implicit COB-CRT-STATUS identifier (with a PICTURE 9(4)) will be allocated for the purpose of receiving screen ACCEPT statuses. If CRT STATUS is specified, then *identifier-1* must be defined in the program as a PICTURE 9(4) field.
- 8. The CURRENCY SIGN clause may be used to redefine the character to be used as a currency sign in a PICTURE (see [PICTURE], page 176) clause. The default currency sign is a dollar-sign ('\$'). You may specify any character except 0-9, A-Z, a-z, +, -, ,, ., *, /, ;, (, ), =, \\, quote ('"') or space.
- 9. The CURSOR IS clause allows you to specify a 4- or 6-character data item into which the cursor screen location at the time a screen ACCEPT is satisfied. The value will be returned as rrcc or rrccc, depending upon the length of the specified identifier-2, where rr and rrr represent the row number (starting at zero) and cc and cc represent the column number (also starting at zero). There is no default data item allocated for this data if the CURSOR IS clause is not specified, and it is the programmer's responsibility to define identifier-2 if the clause is specified.
- 10. The DECIMAL POINT IS COMMA clause reverses the definition of the ',' and '.' characters when they are used as PICTURE editing symbols and within numeric literals. This can have unwanted side-effects see [Punctuation], page 33.
- 11. The LOCALE clause may be used to associate external OS-defined locale names (*literal-2*) with an internal name (*locale-name-1*) that may then be referenced within the program. Locale names are defined by the Operating System and/or C compiler GnuCOBOL will be utilizing on your computer.
- 12. The following is the list of possible locale codes, for example, that would be available on a Windows computer running a GnuCOBOL version that was built utilizing the MinGW Unix-emulator and the GNU C compiler (gcc):
  - A af_ZA, am_ET, ar_AE, ar_BH, ar_DZ, ar_EG, ar_IQ, ar_JO, ar_KW, ar_LB, ar_LY, ar_MA, ar_OM, ar_QA, ar_SA, ar_SY, ar_TN, ar_YE, arn_CL, as_IN, az_Cyrl_AZ, az_Latn_AZ
  - **B** ba_R, be_BY, bg_BG, bn_IN bo_BT, bo_CN, br_FR, bs_Cyrl_BA, bs_Latn_BA
  - C ca_ES, cs_CZ, cy_GB
  - D da_DK, de_AT, de_CH, de_DE, de_LI, de_LU, dsb_DE, dv_MV
  - E el_GR, en_029, en_AU, en_BZ, en_CA, en_GB, en_IE, en_IN, en_JM, en_MY en_NZ, en_PH, en_SG, en_TT, en_US, en_ZA, en_ZW, es_AR, es_BO, es_CL,

es_CO, es_CR, es_DO, es_EC, es_ES, es_GT, es_HN, es_MX, es_NI, es_PA, es_PE, es_PR, es_PY, es_SV, es_US, es_UY es_VE, et_EE, eu_ES

F fa_IR, fi_FI, fil_PH, fo_FO, fr_BE, fr_CA, fr_CH, fr_FR, fr_LU, fr_MC, fy_NL

G ga_IE, gbz_AF, gl_ES, gsw_FR, gu_IN

H ha_Latn_NG, he_IL, hi_IN, hr_BA, hr_HR, hu_HU, hy_AM

I id_ID, ig_NG, ii_CN, is_IS, it_CH, it_IT, iu_Cans_CA, iu_Latn_CA

J ja_JP

K ka_GE, kh_KH, kk_KZ, kl_GL, kn_IN, ko_KR, kok_IN, ky_KG

L lb_LU, lo_LA, lt_LT, lv_LV

 $\label{eq:mi_NZ} \mathbf{M} \qquad \qquad \mathrm{mi_NZ}, \quad \mathrm{mk_MK}, \quad \mathrm{ml_IN}, \quad \mathrm{mn_Cyrl_MN}, \quad \mathrm{mn_Mong_CN} \quad \mathrm{moh_CA}, \quad \mathrm{mr_IN}, \\ \quad \mathrm{ms_BN}, \quad \mathrm{ms_MY}, \quad \mathrm{mt_MT}$ 

N nb_NO, ne_NP, nl_BE, nl_NL, nn_NO, ns_ZA

oc_FR, or_IN

P pa_IN, pl_PL, ps_AF, pt_BR, pt_PT

**Q** qut_GT, quz_BO, quz_EC, quz_PE

R rm_CH, ro_RO, ru_RU, rw_RW

S sa_IN, sah_RU, se_FI, se_NO se_SE, si_LK, sk_SK, sl_SI, sma_NO, sma_SE, smj_NO, smj_SE, smn_FI, sms_FI, sq_AL, sr_Cyrl_BA, sr_Cyrl_CS, sr_Latn_BA, sr_Latn_CS, sv_FI, sv_SE, sw_KE syr_SY

 ${\bf T}$  ta_IN, te_IN, tg_Cyrl_TJ, th_TH tk_TM, tmz_Latn_DZ, tn_ZA, tr_IN, tr_TR, tt_RU

U ug_CN, uk_UA, ur_PK, uz_Cyrl_UZ, uz_Latn_UZ

 $\mathbf{V}$  vi_VN

W wen_DE, wo_SN

 $X xh_-ZA$ 

Y yo_NG

Z zh_CN, zh_HK, zh_MO, zh_SG, zh_TW, zu_ZA

- 13. The NUMERIC SIGN TRAILING SEPARATE specification causes all signed numeric USAGE DISPLAY data items to be created as if the SIGN IS TRAILING SEPARATE CHARACTER clause was included in their definitions.
- 14. The device-name-1 IS mnemonic-name-2 clause allows you to specify an alternate name (device-name-1) for one of the built-in GnuCOBOL device name mnemonic-name-2. The list of device names built-into GnuCOBOL, and the physical device associated with that name, are as follows:

CONSOLE This is the (screen-mode) display of the PC or Unix system.

STDIN

SYSIN

These devices (they are all synonymous) represent standard system input (pipe 0). On a PC or UNIX system, this is typically the keyboard. The contents of a file may be delivered to a GnuCOBOL program for access via one of these device names by adding the sequence '0< filename' to the end of the programs execution command.

PRINTER STDOUT SYSLIST SYSLST

SYSOUT

These devices (they are all synonymous) represent standard system output (pipe 1). On a PC or UNIX system, this is typically the display. Output sent to one of these devices by a GnuCOBOL program can be sent to a file by adding the sequence '1> filename' to the end of the programs execution command.

**STDERR** 

SYSERR

These devices (they are synonymous) represent standard system error output (pipe 2). On a PC or UNIX system, this is typically the display. Output sent to one of these devices by a GnuCOBOL program can be sent to a file by adding the sequence '2> filename' to the end of the programs execution command.

15. The feature-name-1 IS mnemonic-name-3 clause allow for mnemonic names to be assigned to up to the 13 printer channel (i.e. vertical page positioning) position feature names Cnn (nn=01-12) and CSP. Once a channel position has been assigned a mnemonic name, statements of the form WRITE record-name AFTER ADVANCING mnemonic-name-3 may be coded to write the specified print record at the channel position assigned to mnemonic-name-3.

Printers supporting channel positioning are generally mainframe-type line printers. When writing to printers that do not support channel positioning, a formfeed will be issued to the printer.

The CSP positioning option stands for "No Spacing". Testing on a MinGW build of Gnu-COBOL shows that this too results in a formfeed being issued.

#### 5.1.3.1. Alphabet-Name-Clause

### ${\bf SPECIAL\text{-}NAMES} \ {\bf Alphabet\text{-}Clause} \ {\bf Syntax}$ ALPHABET alphabet-name-1 IS { ASCII } } { EBCDIC } { NATIVE { STANDARD-1 } } { STANDARD-2 { Literal-Clause...

#### SPECIAL-NAMES ALPHABET Literal-Clause Syntax

```
literal-1 [{ THRU|THROUGH literal-2 }]
 { ~~~~ ~~~~~
 }
 { {ALSO literal-3}...
```

The ALPHABET clause relates alphabet-name-1 to a specified character code set or collating

sequence, including one you define yourself using the literal-1 option.

- 1. The reserved word IS is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. The reserved words THRU and THROUGH are interchangeable.
- 3. GnuCOBOL considers ASCII, STANDARD-1 and STANDARD-2 to be interchangeable.
- 4. NATIVE specifies the system default character set.
- 5. The following points apply to using the *literal-n* specifications to compose a custom character set:
  - A. The *literal-n* values are either integers or alphanumeric quoted characters. These represent a single character in the NATIVE character set, either by its actual text value (alphanumeric quoted character) or by ordinal position in the NATIVE character set (integer),
  - B. The sequence in which characters are defined in this clause specifies the relative order those characters should have when comparisons are made using this alphabet.
  - C. Character positions in this list do not affect the actual binary storage values used for the characters. Binary values will still be those of the NATIVE character set.
  - D. You may specify any of the figurative constants SPACE, SPACES, ZERO, ZEROS, ZEROES, QUOTE, QUOTES, HIGH-VALUE, HIGH-VALUES, LOW-VALUE or LOW-VALUES for any of the literal-1, literal-2 or literal-3 specifications.

6. Once you have defined an alphabet name, that alphabet name may be used on specifications in CODE-SET, COLLATING SEQUENCE, or SYMBOLIC CHARACTERS clauses elsewhere in the program.

#### 5.1.3.2. Class-Definition-Clause

#### SPECIAL-NAMES Class-Definition-Clause Syntax

```
CLASS class-name-1 IS { literal-1 [THRU|THROUGH literal-2] }...
```

1. The reserved word IS is optional and may be omitted. The presence or absence of this word has no effect upon the program.

- 2. The reserved words THRU and THROUGH are interchangeable.
- 3. Both literal-1 and literal-2 must be alphanumeric literals of length 1.
- 4. The literal(s) specified on this clause define the possible characters that may be found in a data item's value in order to be considered part of the class.
- 5. For example, the following defines a class called Hexadecimal, the definition of which specifies the only characters that may be present in an alphanumeric data item if that data item is to be part of the Hexadecimal class:

```
CLASS Hexadecimal IS '0' THRU '9'
'A' THRU 'F'
'a' THRU 'f'
```

6. Once class Hexadecimal has been defined, program code could then use a statement such as IF input-item IS Hexadecimal to determine if the value of characters in a data item are valid according to that class.

#### 5.1.3.3. Switch-Definition-Clause

#### SPECIAL-NAMES Switch-Definition-Clause Syntax

The switch-definition clause associates a condition-name with a run-time execution switch so that the status of that switch may be tested from within a program.

- 1. The reserved words IS and STATUS are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The valid switch-name-1 names are SWITCH-n (n = 0-36).
- 3. If the program is compiled with the -fsyntax-extension switch, the switch names SWn (n=0-15) are also valid; they correspond to SWITCH-0 through SWITCH-15, respectively as well as SWITCH-16 through SWITCH-36, SWITCH 0 through SWITCH 26 and SWITCH A through SWITCH Z.
- 4. At execution time, each switch will be associated with a COB_SWITCH_n run-time environment variable, where n will have the value '0' through '15'. Any of these sixteen environment variables that have the value ON (regardless of upper- or lower-case value) will be considered to be set "on". Any of these sixteen environment variables having no value at all or a value other than ON will be considered OFF.
- 5. Each specified switch must have at least one of a IS mnemonic-name-1, ON STATUS or an OFF STATUS option defined for it, otherwise there will be no way to reference the switch from within a GnuCOBOL program.
- 6. The IS mnemonic-name-1 syntax provides a means for setting the switch to either an ON or OFF value via the SET statement (see [SET], page 330).
- 7. The ON STATUS and OFF STATUS syntax provides a way of associating a condition-name with either the on or off status of the switch, so that status may be tested at execution time via the IF statement (see [IF], page 291).

#### 5.1.3.4. Symbolic-Characters-Clause

SYMBOLIC CHARACTERS

#### SPECIAL-NAMES-Symbolic-Characters-Clause Syntax

```
{ symbolic-character-1... IS|ARE integer-1... }...
```

This clause may be used to define your own figurative constants.

- 1. The reserved words ARE, CHARACTERS and IS are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. There must be exactly as many *integer-1* values specified as there are *symbolic-character-1* names.
- 3. Each symbolic character name will be associated with the corresponding *integer-1*th character in the alphabet named in the IN clause. The integer values are selecting characters from the alphabet by their ordinal position and not by their numeric value; thus, an integer of 15 will select the 15th character in the specified alphabet, regardless of the actual numeric value of the bit pattern that constitutes that character.
- 4. If no alphabet-name-1 is specified, the systems native character set will be assumed.
- 5. The following two code examples define the same set of figurative constant names for five ASCII control characters (assuming that ASCII is the system's native character set). The two examples are identical in their effects, even though the way the figurative constants are defined is different.

Individually

```
SYMBOLIC CHARACTERS NUL IS 1
SOH IS 2
BEL IS 8
DC1 IS 18
DC2 IS 19
```

Respectively

```
SYMBOLIC CHARACTERS NUL SOH BEL DC1 DC2

ARE 1 2 8 18 19
```

#### 5.1.4. REPOSITORY

# 

The REPOSITORY paragraph provides a way to control access to the various built-in intrinsic functions and any user defined functions that your program will be using.

- 1. The REPOSITORY paragraph is not allowed in a nested subprogram. A nested program inherits the REPOSITORY settings of its parent program.
- 2. The INTRINSIC clause allows you to flag one or more (or ALL) built-in intrinsic functions as being usable without the need to code the keyword FUNCTION in front of the function names.
- 3. As an alternative to using the ALL INTRINSIC clause, you may instead compile your Gnu-COBOL programs using the -fintrinsics=ALL switch.
- 4. The function-prototype-name-1 option is required to specify the name of a user-defined function your program will be using. Optionally, should you desire, you may specify an alias name by which you will reference that user-defined function. Should you wish, you may also use the AS clause to provide an alias name for a built-in intrinsic function.
- 5. The following example
  - enables all intrinsic functions to be specified without the use of the FUNCTION keyword,
  - $\bullet$  names two user-defined functions named MY-FUNCTION-1 and MY-FUNCTION-2 that will be used by the program and
  - specifies the alias names SIGMA for the intrinsic function STANDARD-DEVIATION and MF2 for MY-FUNCTION-2.

```
REPOSITORY.

FUNCTION ALL INTRINSIC.

FUNCTION MY-FUNCTION-1.

FUNCTION MY-FUNCTION-2 AS "MF2".

FUNCTION STANDARD-DEVIATION AS "SIGMA".
```

A special note about user-defined functions — because you must name a user-defined function that your program will be using in the REPOSITORY paragraph, you may always reference that function from your program's procedure division without needing to use the FUNCTION keyword.

#### 5.2. INPUT-OUTPUT SECTION

#### INPUT-OUTPUT SECTION Syntax

The INPUT-OUTPUT section provides for the definition of any files the program will be accessing as well as control of the I/O buffering process against those files through the FILE-CONTROL and I-O-CONTROL paragraphs, respectively.

- 1. As the diagram shows, there are three types of statements that may occur in the two paragraphs of this section. If none of the statements are coded in a particular paragraph, the paragraph itself may be omitted, otherwise it is required.
- 2. If neither paragraph is coded, the INPUT-OUTPUT SECTION. header itself may be omitted, otherwise it is normally required.
- 3. If the compiler *configuration file* (see [Compiler Configuration Files], page 574) you are using has relaxed-syntax-check set to 'yes', the FILE-CONTROL and I-O-CONTROL paragraphs may be specified without the INPUT-OUTPUT SECTION header having been coded.
- 4. If both statement types are coded in the I-O-CONTROL paragraph, the order in which those statements are coded is irrelevant.

#### 5.2.1. SELECT

### **SELECT Statement Syntax** SELECT [ [ NOT ] OPTIONAL ] file-name-1 ~ ~ ~ [ ASSIGN { TO }] [{ identifier-1 }] ] } { word-1 } { DYNAMIC } { DISPLAY } { literal-1 } { ~~~~~ } { KEYBOARD } } { LINE ADVANCING } { ~~~~ ~~~~~~ } { PRINTER { ~~~~~~ } } { RANDOM } { TAPE } [ COLLATING SEQUENCE IS alphabet-name-1 ] [ FILE|SORT ] STATUS IS identifier-2 [ identifier-3 ] ] ~~~~~ [ LOCK MODE IS { MANUAL|AUTOMATIC } ] { ~~~~~ { EXCLUSIVE [ WITH { LOCK ON MULTIPLE RECORDS } ] } { ~~~~ ~~ ~~~~~ } { LOCK ON RECORD } } { ROLLBACK } { ~~~~~ } [ ORGANIZATION Clause ] ~~~~~~~~~~~ [ ORGANISATION Clause ] [ RECORD DELIMITER IS STANDARD-1 ] ~~~~~ ~~~~~~~ [ RESERVE integer-1 AREAS ] [ SHARING WITH { ALL OTHER } ] { ~~~ } { NO OTHER } { READ ONLY }

The COLLATING SEQUENCE, RECORD DELIMITER, RESERVE and ALL OTHER clauses are syntactically recognized but are otherwise non-functional.

The SELECT statement creates a definition of a file and links that COBOL definition to the external operating system environment.

- 1. The reserved words AREAS, IS, MODE, OTHER, SEQUENCE, TO, USING and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. After file-name-1, the various clauses may be coded in any sequence.
- 3. A period must follow the last coded clause.
- 4. The OPTIONAL clause, to be used only for files that will be used to provide input data to the program, indicates the file may or may not actually be available at run-time. Attempts to OPEN an OPTIONAL file when the file does not exist will receive a special non-fatal file status value (see status 05 in the list of file status values below) indicating the file is not available; a subsequent attempt to READ that file will return an AT END (end-of-file) condition. Optionally, files may be designated as NOT OPTIONAL, if desired. This is useful when specifying the compiler's -foptional-file switch, which automatically makes all files OPTIONAL except for those explicitly declared as NOT OPTIONAL.
- 5. The file-name-1 value that you specify will be the name by which you will reference the file within your program. This name should be formed according to the rules for user-defined names (see [User-Defined Words], page 10).
- 6. The optional ASSIGN clause specifies how at runtime, when *file-name-1* is opened either a logical device (STDIN, STDOUT) or a file anywhere in one of the currently-mounted file systems will be associated with *file-name-1*, as follows:
  - A. There are three components to the ASSIGN clause:

Type EXTERNAL, DYNAMIC or neither

Device the list of device choices

Locator shown as a choice between identifier-1, word-1 and literal-1.

- B. ASSIGN TO DISC file-name-1 will be assumed if there is no ASSIGN clause on a SELECT.
- C. If an ASSIGN clause is coded without a Device, the device DISC will be assumed.
- D. If a Locator clause is coded, the COBOL file file-name-1 will be attached to a data file within any file system that is mounted and available to the executing program at the time file-name-1 is opened. How that file is identified varies, depending upon the specified Locator, as follows:
  - a. If *literal-1* is coded, the value of the literal will serve as the File Location String that will identify the data file.
  - b. If identifier-1 is coded, the value of the identifier will serve as the File Location String that will identify the data file.
  - c. If word-1 (a syntactically valid word not duplicating a reserved or user-defined word) is coded, and a Type is EXTERNAL, then word-1 itself will serve as the File Location String that will identify the data file. If, however, a Type of EXTERNAL was not specified, the compiler will create a PIC X(1024) data item named word-1 within the program; the contents of that data item at the time the program opens file-name-1 will then serve as the File Location String that will identify the data file.
  - d. File Location Strings will be discussed shortly.
- E. If no *Locator* is coded, *file-name-1* will be attached to a logical device or a file based upon the specified (or implied) *Device*, as follows:
  - a. DISC or DISK will assume an attachment to a file named file-name-1 in whatever directory is current at the time the file is opened.

- b. DISPLAY will assume an attachment to the STDOUT logical device; these files should only be used for output.
- c. KEYBOARD will assume an attachment to the STDIN logical device; these files should only be used for input.
- d. PRINTER will assume an attachment to the LPT1 logical device/port; these files should only be used for output.
- e. RANDOM or TAPE will behave exactly as DISC does. These two additional *Devices* are provided to facilitate the compilation of COBOL source from other COBOL implementations.
- F. The LINE ADVANCING device requires that a Locator be specified; these files should only be used for output. A COBOL Line Advancing file will allow carriage-control characters such as line-feeds and form-feeds to be written to the attached operating system file, via the ADVANCING clause of the WRITE statement (see [WRITE], page 360).
- G. File Location Strings are used (at runtime) to identify the path and filename to the data file that must be attached to file-name-1 when that file is opened.
- H. If the compiler *configuration file* (see [Compiler Configuration Files], page 574) you used to compile the program with had a filename-mapping value of yes, the GnuCOBOL runtime system will first attempt to identify a currently-defined environment variable whose value will serve as the data file's path and filename, as follows:
  - a. If the compiler configuration file (see [Compiler Configuration Files], page 574) (see [Compiler Configuration Files], page 574) you used to compile the program specified mf as the assign-clause value, then the File Locator String will be interpreted according to Microfocus COBOL rules namely, everything before the last '-' in the File Locator String will be ignored; the characters after the last '-' will be treated as the base of an environment variable name. If there is no '-' character in the File Locator String then the entire File Locator String will serve as the base of an environment variable name. This is the default behaviour for every config file except ibm.
  - b. If, on the other hand, the compiler configuration file (see [Compiler Configuration Files], page 574) you used to compile the program specified mf as the assign-clause value, then the File Locator String will be interpreted according to according to IBM COBOL rules namely, the File Locator String is expected to be of the form S-xxx or AS-xxx, in which case the xxx will be treated as the base of an environment variable name. If there is no '-' character in the File Locator String then the entire File Locator String will serve as the base of an environment variable name.
  - c. Once an environment variable name base (let's refer to it as bbbb) has been determined, the runtime system will look for the first one of the following environment variables that exists, in this sequence:

DD_bbbb dd_bbbb bbbb

Windows systems are case-insensitive with regard to environment variables, so there is no difference between the first two when using a GnuCOBOL implementation built for either Windows/MinGW or native Windows.

If an environment variable was found, its value will serve as the path and filename to the data file.

I. If no environment variable was found, or the *configuration file* (see [Compiler Configuration Files], page 574) used to compile the program had a filename-mapping value of

- NO, then the File Locator String value will serve as the path and filename to the data file.
- J. Paths and file names may be specified on an absolute (C:\\Data\\datafile.dat, /Data/datafile.dat, ...) or relative to the current directory (Data\\datafile.dat, Data/datafile.dat, ...) basis. If no directory name is included (datafile.dat), the file must be in the current directory.
- 7. The FILE STATUS or SORT STATUS clause (they are both equivalent and only one or the other, if any, should be specified) is used to specify the name of a two-digit numeric data item into which an I/O status code will be saved after every I/O verb that is executed against the file. This does not actually allocate the data item you must define the item yourself somewhere in the data division. Note that the following list is not definitive: more can be added and any tests should include one for non zeros as a catch all. Possible status codes that can be returned to a FILE STATUS data item are as follows:

00	Success
02	Success (Duplicate Record Key Written)
04	Success (Incomplete)
05	Success (Optional File Not Found)
07	Success (No Unit)
10	End of file reached if reading forward or beginning-of-file reached if reading backward
14	Out of key range
21	Key invalid
22	Key already exists
23	Key not found
24	Key boundary violation
30	Permanent I/O error
31	Inconsistent filename
34	Boundary violation
35	File not found
37	Permission denied
38	Closed with lock
39	Conflicting attribute
41	File already open
42	File not open
43	Read not done
44	Record overflow
46	Read error
47	OPEN INPUT denied (insufficient permissions to read file)
48	OPEN OUTPUT denied (insufficient permissions to write to file)

49	$\mathtt{OPEN}\ \mathtt{I-O}\ \mathrm{denied}\ \mathrm{(insufficient\ permissions\ to\ read\ and/or\ write\ file)}$
51	Record locked
52	End of page
57	LINAGE bad specification (I-O linage)
61	File sharing failure
71	Bad character
91	File not available

- 8. The SHARING clause defines the conditions under which the program will be willing (or not) to allow other programs executing at the same time to access the file. See [File Sharing], page 52, for the details.
- 9. The LOCK clause defines how concurrent access to the file will be managed on a record-by-record basis. See [Record Locking], page 54, for the details.
- 10. For syntax details for the ORGANIZATION clause, see next group of paragraphs.
- 11. A SELECT statement without an ORGANIZATION explicitly coded will be handled as if the following ORGANIZATION clause had been specified:

ORGANIZATION IS SEQUENTIAL ACCESS MODE IS SEQUENTIAL

# 5.2.1.1. ORGANIZATION SEQUENTIAL

#### **ORGANIZATION SEQUENTIAL Clause Syntax**

```
[ORGANIZATION|ORGANISATION IS] RECORD BINARY SEQUENTIAL

[ACCESS MODE IS SEQUENTIAL]
```

Files declared as ORGANIZATION SEQUENTIAL will consist of records with no explicit end-of-record delimiter character sequences; records in such files are "delineated" by a calculated byte-offset (based on the maximum record length) into the file.

- 1. The reserved words BINARY, IS, MODE and RECORD are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved words ORGANIZATION and ORGANISATION are interchangeable.
- 3. The phrase ORGANIZATION IS (and its internationalized alternative, ORGANISATION IS) is optional to provide compatibility with those (few) COBOL implementations that consider ORGANIZATION to be optional. Most COBOL implementations do require the word ORGANIZATION, so it should be used in new programs.
- 4. These files cannot be prepared with any standard text-editing or word processing software as all such programs will embed delimiter characters at the end of records (use ORGANIZATION IS LINE SEQUENTIAL instead).
- 5. These files may contain either USAGE DISPLAY or USAGE COMPUTATIONAL (of any variety) data since no binary data sequence can be accidentally interpreted as an end-of-record delimiter.
- 6. While records in a ORGANIZATION SEQUENTIAL file may be defined as having variable-length records, the file will be structured in such a manner as to reserve space for each record equal to the size of the largest possible record, based on the file's description in the FILE SECTION.
- 7. The ACCESS MODE SEQUENTIAL clause is optional because, if absent, it will be assumed anyway for this type of file. The internal structure of these files is such that they can only be processed in a sequential manner; in order to read the 100th record in such a file, for example, you first must read records 1 through 99.
- 8. Sequential files are processed using the following statements:
  - CLOSE (see [CLOSE], page 258)
  - COMMIT (see [COMMIT], page 259)
  - DELETE (see [DELETE], page 262)
  - MERGE (see [MERGE], page 302)
  - OPEN (see [OPEN], page 309)
  - READ (see [READ], page 316)
  - REWRITE (see [REWRITE], page 324)
  - SORT (see [SORT], page 339)
  - UNLOCK (see [UNLOCK], page 355)
  - WRITE (see [WRITE], page 360)

# 5.2.1.2. ORGANIZATION LINE SEQUENTIAL

#### ORGANIZATION LINE SEQUENTIAL Clause Syntax

```
[ORGANIZATION|ORGANISATION IS] LINE SEQUENTIAL

[ACCESS MODE IS SEQUENTIAL]

[PADDING CHARACTER IS literal-1 | identifier-1]
```

The PADDING CHARACTER clause is syntactically recognized but is otherwise non-functional.

Files declared as ORGANIZATION LINE SEQUENTIAL will consist of records terminated by an end-of-record delimiter character or character sequence.

- 1. The reserved words CHARACTER, IS and MODE are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved words ORGANIZATION and ORGANISATION are interchangeable.
- 3. The phrase ORGANIZATION IS (and its internationalized alternative, ORGANISATION IS) is optional to provide compatibility with those (few) COBOL implementations that consider that word to be optional. Most COBOL implementations do require the word ORGANIZATION, so it should be used in new programs.
- 4. This is the only ORGANIZATION valid for files that are assigned to the PRINTER device.
- 5. These files may be created with any standard text-editing or word processing software capable of writing text files. Such files should not contain any USAGE COMPUTATIONAL or BINARY (of any variety) data since such fields could accidentally contain byte sequences that could be interpreted as an end-of-record delimiter.
- 6. Both fixed- and variable-length record formats are supported.
- 7. The end-of-record delimiter sequence will be X'OA' (an ASCII line-feed character) or a X'ODOA' (an ASCII carriage-return + line-feed sequence). The former is used on Unix implementations of GnuCOBOL (including Windows/MinGW, Windows/Cygwin and OSX implementations) while the latter would be used with native Windows implementations.
- 8. When reading a LINE SEQUENTIAL file, records in excess of the size implied by the file's description in the FILE SECTION will be truncated while records shorter than that size will be padded to the right with SPACES.
- 9. The ACCESS MODE SEQUENTIAL clause is optional because, if absent, it will be assumed anyway for this type of file. The internal structure of these files is such that the data can only be processed in a sequential manner; in order to read the 100th record in such a file, for example, you first must read records 1 through 99.
- 10. Files assigned to PRINTER or CONSOLE should be specified as ORGANIZATION LINE SEQUENTIAL.
- 11. Line Sequential files are processed using the following statements:
  - CLOSE (see [CLOSE], page 258)
  - COMMIT (see [COMMIT], page 259)
  - DELETE (see [DELETE], page 262)
  - MERGE (see [MERGE], page 302)

- $\bullet$  OPEN (see [OPEN], page 309)
- READ (see [READ], page 316)
- REWRITE (see [REWRITE], page 324)
- SORT (see [SORT], page 339)
- UNLOCK (see [UNLOCK], page 355)
- WRITE (see [WRITE], page 360)

#### 5.2.1.3. ORGANIZATION RELATIVE

#### **ORGANIZATION RELATIVE Clause Syntax**

These files are files with an internal organization such that records may be processed in a sequential manner based upon their physical location in the file or in a random manner by allowing records to be read, written or updated by specifying the relative record number in the file

- 1. The reserved words IS, KEY and MODE are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved words ORGANIZATION and ORGANISATION are interchangeable.
- 3. The phrase ORGANIZATION IS (and its internationalized alternative, ORGANISATION IS) is optional to provide compatibility with those (few) COBOL implementations that consider that word to be optional. Most COBOL implementations do require the word ORGANIZATION, so it should be used in new programs.
- 4. ORGANIZATION RELATIVE files cannot be assigned to the CONSOLE, DISPLAY, LINE ADVANCING or PRINTER devices.
- 5. The RELATIVE KEY clause is optional only if ACCESS MODE SEQUENTIAL is specified.
- 6. While an ORGANIZATION RELATIVE file may be defined as having variable-length records, the file will be structured in such a manner as to reserve space for each record equal to the size of the largest possible record as defined by the file's description in the FILE SECTION.
- 7. ACCESS MODE SEQUENTIAL, the default ACCESS MODE if none is specified, indicates that the records of the file will be processed in a sequential manner, according to their physical sequence in the file.
- 8. ACCESS MODE RANDOM means that records will be processed in random sequence by specifying their record number in the file every time the file is read or written.
- 9. ACCESS MODE DYNAMIC indicates the program may switch back and forth between SEQUENTIAL and RANDOM mode during execution. The file starts out initially in SEQUENTIAL mode when first opened but the program may use the START statement (see [START], page 343) to switch between sequential and random access.
- 10. The RELATIVE KEY data item is a numeric data item that cannot be defined as a field within records of this file. Its purpose is to return the current relative record number of a relative file that is being processed in SEQUENTIAL access mode and to serve as a key that specifies the relative record number to be read or written when processing a relative file in RANDOM access mode.

- 11. Relative files are processed using the following statements:
  - CLOSE (see [CLOSE], page 258)
  - COMMIT (see [COMMIT], page 259)
  - DELETE (see [DELETE], page 262)
  - MERGE (see [MERGE], page 302), ACCESS MODE RANDOM not allowed
  - OPEN (see [OPEN], page 309)
  - READ (see [READ], page 316)
  - REWRITE (see [REWRITE], page 324)
  - SORT (see [SORT], page 339), ACCESS MODE RANDOM not allowed
  - START (see [START], page 343)
  - UNLOCK (see [UNLOCK], page 355)
  - WRITE (see [WRITE], page 360)

#### 5.2.1.4. ORGANIZATION INDEXED

#### **ORGANIZATION INDEXED Clause Syntax**

```
[ORGANIZATION|ORGANISATION IS] INDEXED
 [ACCESS MODE IS { SEQUENTIAL }]
 { ~~~~~ }
 { DYNAMIC
 }
 { ~~~~~
 }
 }
 { RANDOM
]
 [RECORD KEY IS { [data-name-1
 { [record-kev-name-1]
 [=|{SOURCE IS} data-name-2] ...] }
 [ALTERNATE RECORD KEY IS { [data-name-3
    ~~~~~~~~ ~~~~~
                          { [ record-key-name-2 ]
                            [ = | {SOURCE IS} data-name-4 ] ... ] }
                          [ WITH DUPLICATES ] ]...
                          [ SUPPRESS WHEN ALL literal
                                                      ٦
                          [ SUPPRESS WHEN SPACES | ZEROES ]
```

Indexed files, like relative files, may have their records processed in either a sequential or random manner. Unlike relative files, however, the actual location of a record in an indexed file is calculated automatically based upon the value(s) of one or more alphanumeric fields within records of the file. For example, an indexed file containing product data might use the product identification code as a record key. This means you may read, write or update the A6G4328th record or the Z8X7723th record directly, based upon the product id value of those records!

- 1. The reserved words IS, KEY and MODE are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved words ORGANIZATION and ORGANISATION are interchangeable.
- 3. The phrase ORGANIZATION IS (and its internationalized alternative, ORGANISATION IS) is optional to provide compatibility with those (few) COBOL implementations that consider that word to be optional. Most COBOL implementations do require the word ORGANIZATION, so it should be used in new programs.
- 4. ORGANIZATION INDEXED files cannot be assigned to CONSOLE, DISPLAY, KEYBOARD, LINE ADVANCING or PRINTER.
- 5. ACCESS MODE SEQUENTIAL, the default ACCESS MODE if none is specified, indicates that the records of the file will be processed in a sequential manner with respect to the values of the RECORD KEY or the ALTERNATE RECORD KEY most-recently referenced on a START statement (see [START], page 343).

- 6. ACCESS MODE RANDOM means that records will be processed in random sequence by accessing the record with specific record key or alternate record key values.
- 7. ACCESS MODE DYNAMIC allows the file will be processed either in RANDOM or SEQUENTIAL mode; the program may switch between the two modes as needed. The START statement is used to make the switch between modes.
- 8. The RECORD KEY clause defines the field within the record used to provide the primary access to records within the file. No two records in the file will be allowed to have the same PRIMARY KEY field value. The SOURCE IS clause is for use with Split Keys.
- 9. The ALTERNATE RECORD KEY clause, if used, defines an additional field within the record that provides an alternate means of directly accessing records or an additional field by which the file's contents may be processed sequentially. You have the choice of allowing records to have duplicate alternate key values, if necessary.
- 10. There may be multiple ALTERNATE RECORD KEY clauses, each defining an additional alternate key for the file.
- 11. Usage of the SUPPRESS WHEN clause is used when Sparse Keys are required which may take the form for a literal or spaces or zeroes.
- 12. Indexed files are processed using the following statements:
  - CLOSE (see [CLOSE], page 258)
  - COMMIT (see [COMMIT], page 259)
  - DELETE (see [DELETE], page 262)
  - MERGE (see [MERGE], page 302), ACCESS MODE RANDOM not allowed
  - OPEN (see [OPEN], page 309)
  - READ (see [READ], page 316)
  - REWRITE (see [REWRITE], page 324)
  - SORT (see [SORT], page 339), ACCESS MODE RANDOM not allowed
  - START (see [START], page 343)
  - UNLOCK (see [UNLOCK], page 355)
  - WRITE (see [WRITE], page 360)

#### 5.2.2. SAME RECORD AREA

# I-O-CONTROL SAME AREA Syntax SAME { SORT-MERGE } AREA FOR file-name-1...

```
SAME { SURT-MERGE } AREA FUR file-name-1...

""" { """"" }

{ SURT }

{ RECORD }
```

The SAME SORT-MERGE and SAME SORT clauses are syntactically recognized but are otherwise non-functional.

The SAME RECORD AREA clause allows you to specify that multiple files should share the same input and output memory buffers.

- 1. The reserved words AREA and FOR are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. This statement must be terminated with a period.
- 3. While coding only a single file name (the repeated *file-name-1* item) is syntactically valid, this statement will have no effect upon the program unless at least two files are specified.
- 4. The effect of this statement will be to cause the specified files to share the same I/O buffer in memory. These buffers can sometimes get quite large, and by having multiple files share the same buffer memory you may significantly cut down the amount of memory the program is using (thus making "room" for more procedural code or data). If you do use this feature, take care to ensure that no more than one of the specified files are ever OPEN simultaneously.

# 5.2.3. MULTIPLE FILE

# MULTIPLE FILE TAPE CONTAINS { file-name-1 [ POSITION integer-1 ] }... The MULTIPLE FILE TAPE clause is obsolete and is therefore recognized but not functional.

End of Chapter 5 — ENVIRONMENT DIVISION

# 6. DATA DIVISION

#### **DATA DIVISION Syntax**

```
DATA DIVISION.
 ~~~~ ~~~~~~~
[FILE SECTION.
 { File/Sort-Description [{ FILE-SECTION-Data-Item }]... }...]
 {
 { 01-Level-Constant
 }
 }
 {
 }
 }
 { 78-Level-Constant
 }
 { 01-Level-Constant
 }
 { 78-Level-Constant
[WORKING-STORAGE SECTION.
 [{ WORKING-STORAGE-SECTION-Data-Item }]...]
 { 01-Level-Constant
 }
 }
 { 78-Level-Constant
[LOCAL-STORAGE SECTION.
 [{ LOCAL-STORAGE-SECTION-Data-Item }]...]
 { 01-Level-Constant
 }
 }
 { 78-Level-Constant
[LINKAGE SECTION.
 [{ LINKAGE-SECTION-Data-Item }]...]
 { 01-Level-Constant
 }
 }
 { 78-Level-Constant
[REPORT SECTION.
 { Report-Description [{ Report-Group-Definition }]...
 {
 { 01-Level-Constant
 }
 }
 {
 { 78-Level-Constant
 }
 }
 { 01-Level-Constant
 { 78-Level-Constant
[SCREEN SECTION.
 [{ SCREEN-SECTION-Data-Item }]...]
 { 01-Level-Constant
 }
 }
 { 78-Level-Constant
```

All data used by any COBOL program must be defined in one of the six sections of the data division, depending upon the purpose of the data.

- 1. If no data will be described in one of the data division sections, that section header may be omitted.
- 2. If no data division sections are needed, the DATA DIVISION. header itself may be omitted.
- 3. If more than one section is needed in the data division (a common situation), the sections must be coded in the sequence they are presented above.

# 6.1. Data Definition Principles

GnuCOBOL data items, like those of other COBOL implementations, are described in a hierarchical manner. This accommodates the fact that data items frequently need to be able to be broken up into subordinate items. Take for example, the following logical layout of a portion of a data item named Employee:



The Employee data item consists of two subordinate data items — an Employee-Name and an Employment-Dates data item (presumably there would be a lot of others too, but we don't care about them right now). As the diagram shows, each of those data items are, in turn, broken down into subordinate data items. This hierarchy of data items can get rather deep, and GnuCOBOL, like other COBOL implementations, can handle up to 49 levels of such hierarchical structures.

As was presented earlier (see [Structured Data], page 13), a data item that is broken down into other data items is referred to as a group item, while one that isn't broken down is called an elementary item.

COBOL uses the concept of a *level* number to indicate the level at which a data item occurs in a data structure such as the example shown above. When these data items are defined, they are all defined together with a number in the range 1-49 specified in front of their names. Over the years, a convention has come to exist among COBOL programmers that level numbers are always coded as two-digit numbers — they don't *need* to be specified as two-digit numbers, but every example you see in this document will take that approach!

The data item at the top, also referred to as a *record*, always has a level number of 01. After that, you may assign level numbers as you wish (01-02-03-04..., 01-05-10-15..., etc.), as long as you follow these simple rules:

- 1. Every data item at the same *level* of a hierarchy diagram such as the one you see here (if you were to make one, which you rarely will, if ever, once you get used to this concept) must have the same level number.
- 2. Every new level uses a level number that is strictly greater than the one used in the parent (next higher) level.
- 3. When describing data hierarchies, you may never use a level number greater than 49 (except for 66, 77, 78 and 88 which have very special meanings (see [Special Data Items], page 133).

So, the definition of these data items in a GnuCOBOL program would go something like this:

- 01 Employee
  - 05 Employee-Name
    - 10 Last-Name
    - 10 First-Name
    - 10 Middle-Initial
  - 05 Employment-Dates
    - 10 From-Date

15 Year

15 Month

15 Day

10 To-Date

15 Year

15 Month

15 Day

The indentation is purely at the discretion of the programmer to make things easier for humans to read (the compiler couldn't care less). Historically, COBOL implementations that required Fixed Format Mode source programs required that the 01 level number begin in Area A and that everything else begins in Area B. GnuCOBOL only requires that all data definition syntax occur in columns 8-72. In Free Format Mode, of course, there aren't even those limitations.

Did you notice that there are two each of Year, Month and Day data names defined? That's perfectly legal, provided that each can be uniquely qualified so as to be distinct from the other. Take for example the Year items. One is defined as part of the From-Date data item while the other is defined as part of the To-Date data item. In COBOL, we would actually code references to these two data items as either Year OF From-Date and Year OF To-Date or Year IN From-Date and Year IN To-Date (COBOL allows either IN or OF to be used). Since these references would clarify any confusion to us as to which Year might be referenced, the GnuCOBOL compiler won't be confused either.

The coding example shown above is incomplete; it only describes the data item names and their hierarchical relationships to one other. In addition, any valid data item definitions will also need to describe what type of data is to be contained in a data item (Numeric? Alphanumeric? Alphabetic?), how much data can be held in the data item and a multitude of other characteristics.

When group items are being defined, subordinate items may be assigned the "name" FILLER. There may be any number of FILLER items defined within a group item. A data item named FILLER cannot be referenced directly; these items are generally used to specify an unused portion of the total storage allocated to a group item. Note that it is possible that the name of the group item itself might be specified as FILLER if there is no need to ever refer directly to the group structure itself.

# 6.2. FILE SECTION

#### 

Every file that has been referenced by a SELECT statement (see [SELECT], page 95) must also be described in the file section of the data division.

Files destined for use as sort/merge work files must be described with a Sort/Merge File Description (SD) while every other file is described with a File Description (FD). Each of these descriptions will almost always be followed with at least one record description.

# 6.2.1. File/Sort-Description

```
File/Sort-Description Syntax
FD|SD file-name-1 [IS EXTERNAL|GLOBAL]
                       ~~~~~~~ ~~~~
[ BLOCK CONTAINS [ integer-1 TO ] integer-2 CHARACTERS|RECORDS ]
[ CODE-SET IS alphabet-name-1 ]
[ DATA { RECORD IS } identifier-1... ]
  ~~~~ { ~~~~~~
 { RECORDS ARE }
[LABEL { RECORD IS } OMITTED|STANDARD]
 ····· { ······ } ·······
 { RECORDS ARE }
[LINAGE IS integer-3 | identifier-2 LINES
 [LINES AT BOTTOM integer-4 | identifier-3]
 [LINES AT TOP integer-5 | identifier-4]
 [WITH FOOTING AT integer-6 | identifier-5]]
[RECORD { CONTAINS [integer-7 TO] integer-8 CHARACTERS
 }]
 }
 { IS VARYING IN SIZE
 }
 {
 }
 {
 [FROM [integer-7 TO] integer-8 CHARACTERS }
 {
 }
 DEPENDING ON identifier-6]
 }
[RECORDING MODE IS recording-mode]
[{ REPORT IS } report-name-1...]
 { ~~~~~
 { REPORTS ARE }
[VALUE OF implementor-name-1 IS literal-1 | identifier-7] .
```

The BLOCK CONTAINS, DATA RECORD, LABEL RECORD, RECORDING MODE and VALUE OF clauses are syntactically recognized but are obsolete and non-functional. These clauses should not be coded in new programs.

^{1.} The reserved words ARE, AT, CHARACTERS (RECORD clause only), CONTAINS, FROM, IN, IS, ON and WITH are optional and may be included, or not, at the discretion of the programmer. The presence or absence of these words has no effect upon the program.

- 2. The terms RECORD IS and RECORDS ARE are interchangeable.
- 3. The terms REPORT IS and REPORTS ARE are interchangeable.
- 4. Only files intended for use as work files for either the SORT (see [SORT], page 339) or MERGE (see [MERGE], page 302) statements should be coded with an SD all others should be defined with a FD.
- 5. The sequence in which files are defined via FD or SD, as compared to the sequence in which their SELECT statements were coded, is irrelevant.
- 6. The name specified as *file-name-1* must exactly match the name specified on the file's SELECT statement.
- 7. The CODE-SET clause allows a custom alphabet, defined in the SPECIAL-NAMES (see [SPECIAL-NAMES], page 84) paragraph, to be associated with a file. This clause is valid only when used with sequential or line sequential files.
- 8. The LINAGE clause may only be specified in the FD of a sequential or line sequential file. If used with a sequential file, the organization of that file will be implicitly changed to line sequential. The various components of the LINAGE clause define the layout of printed pages as follows:

#### LINES AT TOP

Number of unused (*i.e.* left blank) lines at the top of every page. The default if this if not specified is zero.

#### LINES AT BOTTOM

Number of unused (i.e. left blank) lines at the bottom of every page. The default if this if not specified is zero.

#### LINAGE IS n LINES

Total number of used/usable lines on the page.

The sum of the previous three specifications should be the total number of possible lines available on one printed page.

#### FOOTING AT

Line number beyond which nothing may be printed except for any footing that is to appear on every page. The default for this if not specified is zero, meaning there will be no footings. This value cannot be larger than the LINAGE IS n LINES value.

- 9. This page structure once defined can be automatically enforced by the WRITE statement (see [WRITE], page 360).
- 10. Specifying a LINAGE clause in an FD will cause the LINAGE-COUNTER special register to be created for the file. This automatically-created data item will always contain the current relative line number on the page being prepared which will serve as the starting point for a WRITE statement.
- 11. The RECORD CONTAINS and RECORD IS VARYING clauses are ignored (with a warning message issued) when used with line sequential files. With other file organizations, these mutually-exclusive clauses define the length of data records within the file. The data item specified as *identifier-6* must be defined within one of the record descriptions of *file-name-1*.
- 12. The REPORT IS clause announces to the compiler that the file will be dedicated to the Report Writer Control System (RWCS); the clause names one or more reports, each to be described in the report section. The following special rules apply when the REPORT clause is used:

- A. The clause may only be specified in the FD of a sequential or line sequential file. If used with a sequential file, the organization of that file will be implicitly changed to line sequential.
- B. The FD cannot be followed by record descriptions. Detailed descriptions of data to be printed to the file will be defined in the REPORT SECTION (see [REPORT SECTION], page 124).
- C. If a LINAGE clause is also specified, Values specified for LINAGE IS and FOOTING AT will be ignored. The values of LINES AT BOTTOM and LINES AT TOP, if any, will be honoured.
- 13. The following special rules apply only to sort/merge work files:
  - A. Sort/merge work files should be assigned to DISK (or DISC) on their SELECT statements.
  - B. Sorts and merges will be performed in memory, if the amount of data being sorted allows.
  - C. Should actual disk work files be necessary due to the amount of data being sorted or merged, they will be automatically allocated to disk in a folder defined by:
    - The TMPDIR run-time environment variable (see [Run Time Environment Variables], page 584)
    - The TMP run-time environment variable
    - The TEMP run-time environment variable

(in that order).

- D. These disk files will be automatically purged upon SORT or MERGE termination. They will also be purged if the program terminates abnormally before the SORT or MERGE finishes. Should you ever need to know, temporary sort/merge work files will be named cob*.tmp.
- E. If you specify a specific filename in the sort/merge work file's SELECT, it will be ignored.
- 14. See [Data Description Clauses], page 140, for information on the EXTERNAL and GLOBAL options.

#### 6.2.2. FILE-SECTION-Data-Item

#### FILE-SECTION-Data-Item Syntax

```
level-number [identifier-1 | FILLER] [IS GLOBAL|EXTERNAL]
                                            ~~~~~ ~~~~~~
[ BLANK WHEN ZERO ]
[ JUSTIFIED RIGHT ]
[ OCCURS [ integer-1 TO ] integer-2 TIMES
                        UNBOUNDED
                          ~~~~~~~~
 [DEPENDING ON identifier-2]
 [STEP identifier-6]
 [ASCENDING | DESCENDING KEY IS identifier-3]
 [INDEXED BY identifier-4]]
[PICTURE IS picture-string]
[REDEFINES identifier-5]
[SIGN IS LEADING | TRAILING [SEPARATE [CHARACTER]]]
       ~~~~~~ ~~~~~~
[ SYNCRONIZED|SYNCHRONISED [ LEFT|RIGHT ] ]
[ USAGE IS data-item-usage ] . [ FILE-SECTION-Data-Item ]...
```

The LEFT and RIGHT (SYNCRONIZED) clauses are syntactically recognized but are otherwise non-functional.

Every sort file description (SD or FD) must be followed by at least one 01-level data item, except for file descriptions containing the REPORT IS clause. These 01-level data items, in turn, may be broken down into subordinate group and elementary items. An 01-level data item defined here in the file section is also known as a *Record*, even if it is an elementary item, provided that elementary item lacks the CONSTANT attribute.

- 1. The reserved words BY, IS, KEY, ON and WHEN are optional and may be included, or not, at the discretion of the programmer. The presence or absence of these words has no effect upon the program.
- 2. The reserved words SYNCRONIZED and SYNCRONIZED are interchangeable. Both may be abbreviated to SYNC.
- 3. The reserved word PICTURE may be abbreviated to PIC.
- 4. As the syntax diagram shows, the definition of a FILE-SECTION-Data-Item is a recursive one in that there may be any number of such specifications coded following a FD or SD. The first such specification must have a level number of 01, and will describe a specific format of data record within the file. Specifications that follow that one may have level

numbers greater than 01, in which case they are defining a hierarchical breakdown of the record. The definition of a record is terminated when one of the following occurs:

Another 01-level item is found

signifies the start of another record layout for the file.

Another FD or SD is found

marks the completion of the detailed description of the file and begins another.

A division or section header is found

also marks the completion of the detailed description of the file and signifies the end of the file section as well.

- 5. Every FILE-SECTION-Data-Item description must be terminated with a period.
- 6. If there are multiple record descriptions present for a given FD or SD, the one with the longest length will define the size of the record buffer into which a READ statement (see [READ], page 316) or a RETURN statement (see [RETURN], page 323) will deliver data read from the file and from which a WRITE statement (see [WRITE], page 360) or RELEASE statement (see [RELEASE], page 321) statement will obtain the data to be written to the file.
- 7. The various 01-level record descriptions for a file description implicitly share that one common record buffer (thus, they provide different ways to view the structure of data that can exist within the file). Record buffers can be shared between files by using the SAME RECORD AREA (see [SAME RECORD AREA], page 107) clause.
- 8. The only valid level numbers are 01-49, 66, 77, 78 and 88. Level numbers 66, 77, 78 and 88 all have special uses See [Special Data Items], page 133, for details.
- 9. Not specifying an *identifier-1* or FILLER immediately after the level number has the same effect as if FILLER were specified. A data item named FILLER cannot be referenced directly; these items are generally used to specify an unused portion of the total storage allocated to a group item or to describe a group item whose contents which will only be referenced using the names of those items that belong to it.
- 10. EXTERNAL cannot be combined with GLOBAL or REDEFINES.
- 11. File section data buffers (and therefore all 01-level record layouts defined in the file section) are initialized to all binary zeros when the program is loaded into storage.
- 12. See [Data Description Clauses], page 140, for information on the usage of the various data description clauses.

# 6.3. WORKING-STORAGE SECTION

#### WORKING-STORAGE-SECTION-Data-Item Syntax

```
level-number [ identifier-1 | FILLER ] [ IS GLOBAL | EXTERNAL ]
[ BASED ]
[ BLANK WHEN ZERO ]
  ~~~~
[JUSTIFIED RIGHT]
[OCCURS [integer-1 TO] integer-2 TIMES
 UNBOUNDED
 [DEPENDING ON identifier-2]
 [ASCENDING|DESCENDING KEY IS identifier-3]
 [INDEXED BY identifier-4]]
[PICTURE IS picture-string]
[REDEFINES identifier-5]
[SIGN IS LEADING TRAILING [SEPARATE CHARACTER]]
       ~~~~~~ ~~~~~~
[ SYNCRONIZED|SYNCHRONISED [ LEFT|RIGHT ] ]
[ USAGE IS data-item-usage ]
[ VALUE IS [ ALL ] literal-1 ] . [ WORKING-STORAGE-SECTION-Data-Item ]...
```

The LEFT and RIGHT (SYNCRONIZED) clauses are syntactically recognized but are otherwise non-functional.

The working-storage section is used to describe data items that are not part of files, screens or reports and whose data values persist throughout the execution of the program.

- 1. The reserved words BY, CHARACTER, IS, KEY, ON, RIGHT (JUSTIFIED), TIMES and WHEN are optional and may be included, or not, at the discretion of the programmer. The presence or absence of these words has no effect upon the program.
- 2. The reserved words SYNCRONIZED and SYNCHRONISED are interchangeable. Both may be abbreviated as SYNC.
- 3. The reserved word PICTURE may be abbreviated to PIC.
- 4. The reserved word JUSTIFIED may be abbreviated to JUST.
- 5. As the syntax diagram shows, the definition of a WORKING-STORAGE-SECTION-Data-Item is a recursive one in that there may be any number of such specifications coded following one another. The first such specification must have a level number of 01. Specifications that

follow that one may have level numbers greater than 01, in which case they are defining a hierarchical breakdown of a record. The definition of a record is terminated when one of the following occurs:

- Another 01-level item is found this signifies the end of the definition of one record and the start of a another.
- A 77-level item is found this signifies the end of the definition of the record and begins the definition of a special data item; See [77-Level Data Items], page 137, for more information.
- A division or section header is found this also marks the completion of a record and signifies the end of the working-storage section as well.
- 6. Every WORKING-STORAGE-SECTION-Data-Item description must be terminated with a period.
- 7. The only valid level numbers are 01-49, 66, 77, 78 and 88. Level numbers 01 through 49 are used to define data items that may be part of a hierarchical structure. Level number 01 can also be used to define a constant an item with an unchangeable value specified at compilation time.
- 8. Level numbers 66, 77, 78 and 88 all have special uses See [Special Data Items], page 133, for details.
- 9. Not specifying an *identifier-1* or FILLER immediately after the level number has the same effect as if FILLER were specified. A data item named FILLER cannot be referenced directly; these items are generally used to specify an unused portion of the total storage allocated to a group item or to describe a group item whose contents which will only be referenced using the names of those items that belong to it.
- 10. Data items defined within the working-storage section are automatically initialized once—as the program in which the data is defined is loaded into memory. Subprograms may be loaded into memory more than once (see the CANCEL statement (see [CANCEL], page 257)), in which case initialization will happen each time they are loaded. See [Data Initialization], page 23, for a discussion of the initialization rules.
- 11. See [Data Description Clauses], page 140, for information on the usage of the various data description clauses.

# 6.4. LOCAL-STORAGE SECTION

#### LOCAL-STORAGE-SECTION-Data-Item Syntax

```
level-number [ identifier-1 | FILLER ] [ IS GLOBAL|EXTERNAL ]
[ BASED ]
[ BLANK WHEN ZERO ]
  ~~~~
[JUSTIFIED RIGHT]
[OCCURS [integer-1 TO] integer-2 TIMES
 UNBOUNDED
 [DEPENDING ON identifier-2]
 [ASCENDING|DESCENDING KEY IS identifier-3]
 [INDEXED BY identifier-4]]
[PICTURE IS picture-string]
[REDEFINES identifier-5]
[SIGN IS LEADING TRAILING [SEPARATE CHARACTER]]
       ~~~~~~ ~~~~~~
[ SYNCRONIZED|SYNCHRONISED [ LEFT|RIGHT ] ]
[ USAGE IS data-item-usage ]
[ VALUE IS [ ALL ] literal-1 ] . [ LOCAL-STORAGE-SECTION-Data-Item ]...
```

The LEFT and RIGHT (SYNCRONIZED) clauses are syntactically recognized but are otherwise non-functional.

The local-storage section is similar to working-storage, but describes data within a subprogram that will be dynamically allocated and initialized (automatically) each time the subprogram is executed. See [Data Initialization], page 23, for the rules of data initialization.

- 1. The reserved words BY, CHARACTER IS, KEY, ON, RIGHT (JUSTIFIED), TIMES and WHEN are optional and may be included, or not, at the discretion of the programmer. The presence or absence of these words has no effect upon the program.
- 2. The reserved words SYNCRONIZED and SYNCHRONISED are interchangeable. Both may be abbreviated as SYNC.
- 3. The reserved word PICTURE may be abbreviated to PIC.
- 4. The reserved word JUSTIFIED may be abbreviated to JUST.
- 5. As the syntax diagram shows, the definition of a LOCAL-STORAGE-SECTION-Data-Item is a recursive one in that there may be any number of such specifications coded following one

another. The first such specification must have a level number of 01. Specifications that follow that one may have level numbers greater than 01, in which case they are defining a hierarchical breakdown of a record. The definition of a record is terminated when one of the following occurs:

- Another 01-level item is found this signifies the end of the definition of one record and the start of a another.
- A division or section header is found this also marks the completion of a record and signifies the end of the local-storage section as well.
- 6. Every LOCAL-STORAGE-SECTION-Data-Item description must be terminated with a period.
- 7. The only valid level numbers are 01-49, 66, 77, 78 and 88. Level numbers 01 through 49 are used to define data items that may be part of a hierarchical structure. Level number 01 can also be used to define a constant an item with an unchangeable value specified at compilation time.
- 8. Level numbers 66, 77, 78 and 88 all have special uses See [Special Data Items], page 133, for details.
- 9. Not specifying an *identifier-1* or FILLER immediately after the level number has the same effect as if FILLER were specified. A data item named FILLER cannot be referenced directly; these items are generally used to specify an unused portion of the total storage allocated to a group item or to describe a group item whose contents which will only be referenced using the names of those items that belong to it.
- 10. Local-storage cannot be used in nested subprograms.
- 11. See [Data Description Clauses], page 140, for information on the usage of the various data description clauses.

# 6.5. LINKAGE SECTION

#### LINKAGE-SECTION-Data-Item Syntax

```
level-number [ identifier-1 | FILLER ] [ IS GLOBAL|EXTERNAL ]
[ ANY LENGTH ]
[ BASED ]
  ~ ~ ~ ~ ~
[ BLANK WHEN ZERO ]
[ JUSTIFIED RIGHT ]
[ OCCURS [ integer-1 TO ] integer-2 TIMES
      [ DEPENDING ON identifier-3 ]
      [ ASCENDING | DESCENDING KEY IS identifier-4 ]
        ~~~~~~~~ ~~~~~~~~~~
 [INDEXED BY identifier-5]]
[PICTURE IS picture-string]
[REDEFINES identifier-6]
[SIGN IS LEADING | TRAILING [SEPARATE CHARACTER]]
[SYNCRONIZED|SYNCHRONISED [LEFT|RIGHT]]
[USAGE IS data-item-usage] . [LINKAGE-SECTION-Data-Item]...
```

The LEFT and RIGHT (SYNCRONIZED) clauses are syntactically recognized but are otherwise non-functional.

The linkage section describes data within a subprogram that serves as either input arguments to or output results from the subprogram.

- 1. The reserved words BY, CHARACTER, IS, KEY, ON and WHEN are optional and may be included, or not, at the discretion of the programmer. The presence or absence of these words has no effect upon the program.
- 2. The reserved words SYNCRONIZED and "SYNCHRONISED" are interchangeable. Both may be abbreviated as SYNC.
- 3. The reserved word PICTURE may be abbreviated to PIC.
- 4. The reserved word JUSTIFIED may be abbreviated to JUST.
- 5. As the syntax diagram shows, the definition of a LINKAGE-SECTION-Data-Item is a recursive one in that there may be any number of such specifications coded following one another. The first such specification must have a level number of 01. Specifications that follow that one may have level numbers greater than 01, in which case they are defining a hierarchical

breakdown of a record. The definition of a record is terminated when one of the following occurs:

- Another 01-level item is found this signifies the end of the definition of one record and the start of a another.
- A division or section header is found this also marks the completion of a record and signifies the end of the linkage section as well.
- 6. Every LINKAGE-SECTION-Data-Item description must be terminated with a period.
- 7. The only valid level numbers are 01-49, 66, 77, 78 and 88. Level numbers 01 through 49 are used to define data items that may be part of a hierarchical structure. Level number 01 can also be used to define a constant an item with an unchangeable value specified at compilation time.
- 8. Level numbers 66, 77, 78 and 88 all have special uses See [Special Data Items], page 133, for details.
- 9. It is expected that:
  - A. A linkage section should occur only within a subprogram. The compiler will not prevent its use in a main program, however.
  - B. All 01-level data items described within a subprogram's linkage section should appear in a PROCEDURE DIVISION USING (see [PROCEDURE DIVISION USING], page 212) or as arguments on an ENTRY statement.
  - C. Each 01-level data item described within a subprogram's linkage section should correspond to an argument passed on a CALL statement (see [CALL], page 253) or an argument on a function call to the subprogram.
- 10. Not specifying an *identifier-1* or FILLER immediately after the level number has the same effect as if FILLER were specified. A data item named FILLER cannot be referenced directly; these items are generally used to specify an unused portion of the total storage allocated to a group item or to describe a group item whose contents which will only be referenced using the names of those items that belong to it. In the linkage section, 01-level data items cannot be named FILLER.
- 11. No storage is allocated for data defined in the linkage section; the data descriptions there are merely defining storage areas that will be passed to the subprogram by a calling program. Therefore, any discussion of the default initialization of such data is irrelevant. It is possible, however, to manually allocate linkage section data items that aren't subprogram arguments via the ALLOCATE statement (see [ALLOCATE], page 250) statement. In such cases, initialization will take place as per the documentation of that statement.
- 12. See [Data Description Clauses], page 140, for information on the usage of the various data description clauses.

}

}

{

{

# 6.6. REPORT SECTION

{ 01-Level-Constant { 78-Level-Constant

#### REPORT SECTION Syntax [ REPORT SECTION. ~~~~~ ~~~~~ { Report-Description [ { Report-Group-Definition } ]... }... ] { 01-Level-Constant } } { 78-Level-Constant } }

#### Report-Description (RD) Syntax

```
RD report-name [IS GLOBAL]
[CODE IS literal-1 | identifier-1]
[{ CONTROL IS } { FINAL
 { ~~~~~
 { CONTROLS ARE } { identifier-2 }
[PAGE [{ LIMIT IS }] [{ literal-2 } LINES]
 { ~~~~~ }
 { identifier-3 } ~~~~
 { LIMITS ARE }
 [literal-3 | identifier-4 COLUMNS|COLS]
                               ~~~~~~ ~~~
     [ HEADING IS literal-4 | identifier-5 ]
     [FIRST DE|DETAIL IS literal-5 | identifier-6]
     [ LAST CH|{CONTROL HEADING} IS literal-6 | identifier-7 ]
               ~~~~~~ ~~~~~
 [LAST DE|DETAIL IS literal-7 | identifier-8]
 [FOOTING IS literal-8 | identifier-9]] .
```

This section describes the layout of printed reports as well as many of the functional aspects of the generation of reports that will be produced via the Report Writer Control System. It is important to maintain the order of these clauses and ensure that all fields defined or referenced with this section are actually defined in the WORKING-STORAGE SECTION and not elsewhere.

- 1. The reserved words ARE and IS are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The phrases CONTROL IS and CONTROLS ARE are interchangeable, as are the PAGE LIMIT and PAGE LIMITS phrases.

- 3. The reserved word LINES may be abbreviated as LINE.
- 4. The reserved word COLUMNS may be abbreviated as COLS.
- 5. Each report referenced on a REPORT IS clause (see [File/Sort-Description], page 113) must be described with a report description (RD).
- 6. See [GLOBAL], page 161, for information on the GLOBAL option.
- 7. Please see [Report Writer Features], page 22, if you have not read it already. It will familiarize you with the Report Writer terminology that follows.
- 8. The following rules pertain to the PAGE LIMITS clause:
  - A. If no PAGE LIMITS clause is specified, the entire report will be generated as if it consists of a single arbitrarily long page.
  - B. All literals (*literal-2* through *literal-8*) must be numeric with non-zero positive integer values.
  - C. All identifiers (*identifier-2* through *identifier-8*) must be numeric, unedited with non-zero positive integer values.
  - D. Any value specified for *literal-2* or *identifier-2* will define the total number of available lines on any report page, not counting any unused margins at the top and/or bottom of the page (defined by the LINES AT TOP and LINES AT BOTTOM values specified on the LINAGE clause of the FD this RD is linked to see [File/Sort-Description], page 113).
  - E. Any value specified for *literal-3* or *identifier-3* will be ignored.
  - F. The HEADING clause defines the first line number at which a report heading or page heading may be presented.
  - G. The FIRST DETAIL clause defines the first line at which a detail group may be presented.
  - H. The LAST CONTROL HEADING clause defines the last line at which any line of a control heading may be presented.
  - I. The LAST DETAIL clause defines the last line at which any line of a detail group may be presented.
  - J. The FOOTING clause defines the last line at which any line of a control footing group may be presented.
  - K. The following rules establish default values for the various PAGE LIMIT clauses, assuming there is one:

**HEADING** default is one (1)

# FIRST DETAIL HEADING

value is used

#### LAST CONTROL HEADING

value from LAST DETAIL or, if that is absent, the value from FOOTING or, if that too is absent, the value from PAGE LIMIT

#### LAST DETAIL

value from FOOTING or, if that is absent, the value from PAGE LIMIT

FOOTING value from LAST DETAIL or, if that is absent, the value from PAGE LIMIT

- L. For the values specified on a PAGE LIMIT clause to be valid, all of the following must be true:
  - FIRST DETAIL < HEADING
  - LAST CONTROL HEADING ≤ FIRST DETAIL
  - ullet LAST DETAIL  $\leq$  LAST CONTROL HEADING

#### FOOTING ≤ LAST DETAIL

- 9. The following rules pertain to the CONTROL clause:
  - A. If there is no CONTROL clause, the report will contain no control breaks; this implies that there can be no CONTROL HEADING or CONTROL FOOTING report groups defined for this RD.
  - B. Include the reserved word FINAL if you want to include a special control heading before the first detail line is generated (CONTROL HEADING FINAL) or after the last detail line is generated (CONTROL FOOTING FINAL).
  - C. If you specify FINAL, it must be the first control break named in the RD.
  - D. Any *identifier-9* specifications included on the CONTROL clause are referencing data names defined in any data division section except for the report section.
  - E. There must be a CONTROL HEADING and/or CONTROL FOOTING report group defined in the report section for each *identifier-9*.
  - F. At execution time:
    - Each time a GENERATE statement (see [GENERATE], page 286) is executed against a detail report group defined for this RD, the RWCS will check the contents of each *identifier-2* data item; whenever an *identifier-9*'s value has changed since the previous GENERATE, a control break condition will be in effect for that *identifier-2*.
    - Once the list of control breaks has been determined, the CONTROL FOOTING for each *identifier-2* having a control break (if any such report group is defined) will be presented.
    - Next, the CONTROL HEADING for each *identifier-2* having a control break (if any such report group is defined) will be presented.
    - The CONTROL FOOTING and CONTROL HEADING report groups will be presented in the sequence in which they are listed on the CONTROL clause.
    - Only after this processing has occurred will the detail report group specified on the GENERATE be presented.
- 10. Each RD will have the following allocated for it:
  - A. The PAGE-COUNTER special register (see [Special Registers], page 227), which will contain the current report page number.
    - This register will be set to a value of 1 when an INITIATE statement (see [INITIATE], page 296) is executed for the report and will be incremented by 1 each time the RWCS starts a new page of the report.
    - References to PAGE-COUNTER within the report section will be implicitly qualified with the name of the report to which the report group referencing the register belongs.
    - References to PAGE-COUNTER in the procedure division must be qualified with the appropriate report name if there are multiple RDs defined.
  - B. The LINE-COUNTER special register, which will contain the current line number on the current page.
- 11. The RD must be followed by at least one 01-level report group definition.

# 6.6.1. Report Group Definitions

# Report-Group-Definition Syntax

```
01 [identifier-1]
[LINE NUMBER IS { integer-1 [[ON NEXT PAGE] }]
                              ~~~~ ~~~~
                                              }
                {
                { +|PLUS integer-1
                                              }
                { ON NEXT PAGE
[ NEXT GROUP IS { [ + | PLUS ] integer-2 } ]
            { ~~~~
               { NEXT|{NEXT PAGE}|PAGE }
                 ~~~~ ~~~~ ~~~~ ~~~
[TYPE IS { RH|{REPORT HEADING}}
 }]
 { ~~ ~~~~~ ~~~~~
 }
 }
 { PH|{PAGE HEADING}
 { ~~ ~~~~ ~~~~~~~
 }
 { CH|{CONTROL HEADING} FINAL|identifier-2
 }
 { DE|DETAIL
 }
 { ~~ ~~~~~
 }
 { CF|{CONTROL FOOTING} FINAL|identifier-2
 { ~~ ~~~~~ ~~~~~ ~~~~~
 }
 { PF|{PAGE FOOTING}
 }
 ~~ ~~~~ ~~~~~
 }
 { RF|{REPORT FOOTING}
 }
 ~~ ~~~~~ ~~~~~
 [REPORT-SECTION-Data-Item]...
```

The syntax shown here documents how a report group is defined to a report. This syntax is valid only in the report section, and only then after an RD.

- 1. The reserved words IS, NUMBER and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The RH and REPORT HEADING terms are interchangeable, as are PH and PAGE HEADING, CH and CONTROL HEADING, DE and DETAIL, CF and CONTROL FOOTING, PF and PAGE FOOTING as well as RF and REPORT FOOTING.
- 3. The report group being defined will be a part of the most-recently coded RD.
- 4. The TYPE (see [TYPE], page 196) clause specifies the type of report group being defined.
- 5. The level number used for a report group definition must be 01.
- 6. The optional *identifier-1* specification assigns a name to this report group so that the group may be referenced either by a GENERATE statement or on a USE BEFORE REPORTING.
- 7. No two report groups in the same report (RD) may named with the same *identifier-1*. There may, however, be multiple *identifier-1* definitions in different reports. In such instances, references to *identifier-1* must be qualified by the report name.

- 8. There may only be one report heading, report footing, final control heading, final control footing, page heading and page footing defined per report.
- 9. Report group declarations must be followed by at least one REPORT-SECTION-Data-Item with a level number in the range 02-49.
- 10. See [Data Description Clauses], page 140, for information on the usage of the various data description clauses.

#### 6.6.2. REPORT SECTION Data Items

#### **REPORT-SECTION-Data-Item Syntax**

```
level-number [identifier-1]
[BLANK WHEN ZERO]
  ~~~~
            ~~~~
[COLUMN [{ NUMBER IS
 }] [+|PLUS] integer-1]
 { ~~~~~ }
 { NUMBERS ARE }
[GROUP INDICATE]
  ~~~~~ ~~~~~~~
[ JUSTIFIED RIGHT ]
[ LINE NUMBER IS { integer-2 [ [ ON NEXT PAGE ] } ]
                { +|PLUS integer-2 ~~~~ ~~~~
                                             }
                {
                                             }
                { ON NEXT PAGE
                                             }
                    ~~~~ ~~~~
[OCCURS [integer-3 TO] integer-4 TIMES
 [DEPENDING ON identifier-2]
     ~~~~~~~
   [ STEP integer-5 ]
   [ VARYING identifier-3 FROM { identifier-4 } BY { identifier-5 } ]
                         ~~~~ { integer-6 } ~~ { integer-7
[PICTURE IS picture-string]
[PRESENT WHEN condition-name]
  ~~~~~~ ~~~~
[ SIGN IS LEADING | TRAILING [ SEPARATE CHARACTER ] ]
[ { SOURCE IS literal-1|identifier-6 [ ROUNDED ]
                                                                } ]
 { ~~~~~
 { SUM OF { identifier-7 }... [ { RESET ON FINAL|identifier-8 } ] }
 { ~~~ { literal-2 } { ~~~~~
                                                           }
 { VALUE IS [ ALL ] literal-3 { UPON identifier-9
 [ REPORT-SECTION-Data-Item ]...
```

Data item descriptions describing the report lines and fields that make up the substance of a report group immediately follow the definition of that group.

- 1. The reserved words IS, NUMBER, OF, ON, RIGHT, TIMES and WHEN (BLANK) are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved word COLUMN may be abbreviated as COL.
- 3. The reserved word JUSTIFIED may be abbreviated as JUST.

- 4. The reserved word PICTURE may be abbreviated as PIC.
- 5. The SOURCE (see [SOURCE], page 191), SUM (see [SUM], page 450) and VALUE (see [VALUE], page 207) clauses, valid only on an elementary item, are mutually-exclusive of each other.
- 6. Group items (those without PICTURE clauses) are frequently used to describe entire lines of a report, while elementary items (those with a picture clause) are frequently used to describe specific fields of information on the report. When this coding convention is being used, group items will have LINE (see [LINE], page 167) clauses and no COLUMN (see [COLUMN], page 151) clauses while elementary items will be specified the other way around.
- 7. See [Data Description Clauses], page 140, for information on the usage of the various data description clauses.

### 6.7. SCREEN SECTION

### SCREEN-SECTION-Data-Item Syntax

```
level-number [ identifier-1 | FILLER ]
[ AUTO | AUTO-SKIP | AUTOTERMINATE ] [ BELL | BEEP ]
 ~~~~
                ~~~~~~~~~~
[ BACKGROUND-COLOR|BACKGROUND-COLOUR IS integer-1 | identifier-2 ]
 [ BLANK LINE|SCREEN ] [ ERASE EOL|EOS ]
 ~~~~ ~~~ ~~~~
[BLANK WHEN ZERO] [JUSTIFIED RIGHT]
[BLINK] [HIGHLIGHT | LOWLIGHT] [REVERSE-VIDEO]
      ~~~~~~
                              ~~~~~~~~~~
[COLUMN NUMBER IS [+|PLUS] integer-2 | identifier-3]
[FOREGROUND-COLOR|FOREGROUND-COLOUR IS integer-3 | identifier-4]
 [{ FROM literal-1 | identifier-5 }]
 { ~~~~
 { TO identifier-5
 }
 { ~~
 }
 { USING identifier-5
 }
 }
 { VALUE IS [ALL] literal-1
 }
[FULL | LENGTH-CHECK] [REQUIRED | EMPTY-CHECK] [SECURE | NO-ECHO]
 [LEFTLINE] [OVERLINE] [UNDERLINE]
 ~~~~~
[ LINE NUMBER IS [ + | PLUS ] integer-4 | identifier-6 ]
[ OCCURS integer-5 TIMES ]
[ PICTURE IS picture-string ]
[ PROMPT [ CHARACTER IS literal-2 | identifier-7 ]
[ SIGN IS LEADING TRAILING [ SEPARATE CHARACTER ] ]
       [ SCREEN-SECTION-Data-Item ]...
```

The screen section describes the screens to be displayed during terminal/console I-O.

- 1. The reserved words CHARACTER (SEPARATE clause), IS, NUMBER, RIGHT, TIMES and WHEN are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved word COLUMN may be abbreviated as COL.

- 3. The reserved word PICTURE may be abbreviated as PIC.
- 4. The following sets of reserved words are interchangeable:
  - AUTO, AUTO-SKIP and AUTOTERMINATE
  - BACKGROUND-COLOR and BACKGROUND-COLOUR
  - BELL and BEEP
  - FOREGROUND-COLOR and FOREGROUND-COLOUR
  - FULL and LENGTH-CHECK
  - REQUIRED and EMPTY-CHECK
  - SECURE and NO-ECHO
- 5. Data items defined in the screen section describe input, output or combination screen layouts to be used with ACCEPT data-item statement (see [ACCEPT data-item], page 234) or DISPLAY data-item statement (see [DISPLAY data-item], page 268) statements. These screen layouts may define the entire available screen area or any subset of it.
- 6. The term available screen area is a nebulous one in those environments where command-line shell sessions are invoked within a graphical user-interface environment, as will be the case on Windows, OSX and most Unix/Linux systems these environments allow command-line session windows to exist with a variable number of available screen rows and columns. When you are designing GnuCOBOL screens, you need to do so with an awareness of the logical screen row/column geometry the program will be executing within.
- 7. Data items with level numbers 01 (Constants), 66, 78 and 88 may be used in the screen section; they have the same syntax, rules and usage as they do in the other data division sections.
- 8. Without LINE (see [LINE], page 167) or COLUMN (see [COLUMN], page 151) clauses, screen section fields will display on the console window beginning at whatever line/column coordinate is stated or implied by the ACCEPT data-item or DISPLAY data-item statement that presents the screen item. After a field is presented to the console window, the next field will be presented immediately following that field.
- 9. A LINE clause explicitly stated in the definition of a screen section data item will override any LINE clause included on the ACCEPT data-item or DISPLAY data-item statement that presents that data item to the screen. The same is true of COLUMN clauses.
- 10. The Tab and Back-Tab (Shift-Tab on most keyboards) keys will position the cursor from field to field in the line/column sequence in which the fields occur on the screen at execution time, regardless of the sequence in which they were defined in the screen section.
- 11. See [Data Description Clauses], page 140, for information on the usage of the various data description clauses.

### 6.8. Special Data Items

### 6.8.1. 01-Level Constants

```
01-Level-Constant Syntax
01 constant-name-1 CONSTANT [ IS GLOBAL ]
                                              } } .
  { AS { literal-1
       { { BYTE-LENGTH } OF { identifier-1 } } }
  {
       { { ~~~~~~~ } { usage-name
  {
                                            } } }
  {
       { { LENGTH
                       }
                                              } }
  {
                                                 }
                                                 }
  { FROM CDF-variable-name-1
```

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE, SCREEN.

The 01-level constant is one of four types of compilation-time constants that can be declared within a program. The other three types are >>DEFINE CDF directive (see [>>DEFINE], page 63) constants, >>SET CDF directive (see [>>SET], page 66) constants and 78-level constants (see [78-Level Data Items], page 138).

- 1. The reserved words AS, IS and OF are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. See [GLOBAL], page 161, for information on the GLOBAL option.
- 3. This particular type of constant declaration provides the ability to determine the length of a data item or the storage size associated with a particular numeric USAGE (see [USAGE], page 198) type something not possible with the other types of constants.
- 4. Constants defined in this way become undefined once an END PROGRAM or END FUNCTION is encountered in the input source.
- 5. Data descriptions of this form do not actually allocate any storage they merely define a name (constant-name-1) that may be used anywhere a numeric literal (see BYTE-LENGTH or LENGTH options) or a literal of the same type as literal-1 may be used.
- 6. The constant-name-1 name may not be referenced on a CDF directive.
- 7. Care must be taken that *constant-name-1* does not duplicate any other data item name that has been defined in the program as references to that data item name will refer to the constant and not the data item. The GnuCOBOL compiler will not issue a warning about this condition.
- 8. The value specified for *usage-name* may be any USAGE that does not use a PICTURE (see [PICTURE], page 176) clause. These would be any of BINARY-C-LONG, BINARY-CHAR, BINARY-DOUBLE, BINARY-LONG, BINARY-SHORT, COMP-1 (or COMPUTATIONAL-1), COMP-2 (or COMPUTATIONAL-2), FLOAT-DECIMAL-16, FLOAT-DECIMAL-34, FLOAT-LONG, FLOAT-SHORT, POINTER, or PROGRAM-POINTER.
- 9. The BYTE-LENGTH clause will produce a numeric value for *constant-name-1* identical to that which would be returned by the BYTE-LENGTH intrinsic function executed against *identifier-1* or a data item declared with a USAGE of *usage-name*.

10. The LENGTH clause will produce a numeric value for *constant-name-1* identical to that which would be returned by the LENGTH intrinsic function executed against *identifier-1* or a data item declared with a USAGE of *usage-name*.

Here is the listing of a GnuCOBOL program that uses 01-level constants to display the length (in bytes) of the various picture-less usage types.

```
IDENTIFICATION DIVISION.
PROGRAM-ID. Usage-Lengths.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 Len-BINARY-C-LONG
                       CONSTANT AS LENGTH OF BINARY-C-LONG.
01 Len-BINARY-CHAR
                        CONSTANT AS LENGTH OF BINARY-CHAR.
01 Len-BINARY-DOUBLE
                       CONSTANT AS LENGTH OF BINARY-DOUBLE.
01 Len-BINARY-LONG
                       CONSTANT AS LENGTH OF BINARY-LONG.
01 Len-BINARY-SHORT
                       CONSTANT AS LENGTH OF BINARY-SHORT.
                        CONSTANT AS LENGTH OF COMP-1.
01 Len-COMP-1
01 Len-COMP-2
                       CONSTANT AS LENGTH OF COMP-2.
01 Len-FLOAT-DECIMAL-16 CONSTANT AS LENGTH OF FLOAT-DECIMAL-16.
01 Len-FLOAT-DECIMAL-34 CONSTANT AS LENGTH OF FLOAT-DECIMAL-34.
                      CONSTANT AS LENGTH OF FLOAT-LONG.
01 Len-FLOAT-LONG
01 Len-FLOAT-SHORT
                       CONSTANT AS LENGTH OF FLOAT-SHORT.
01 Len-POINTER
                        CONSTANT AS LENGTH OF POINTER.
01 Len-PROGRAM-POINTER CONSTANT AS LENGTH OF PROGRAM-POINTER.
PROCEDURE DIVISION.
000-Main.
   DISPLAY "On this system, with this build of GnuCOBOL, the"
   DISPLAY "PICTURE-less USAGE's have these lengths (in bytes):"
   DISPLAY " "
   DISPLAY "BINARY-C-LONG:
                             " Len-BINARY-C-LONG
   DISPLAY "BINARY-CHAR:
                             " Len-BINARY-CHAR
   DISPLAY "BINARY-DOUBLE:
                             " Len-BINARY-DOUBLE
                            " Len-BINARY-LONG
   DISPLAY "BINARY-LONG:
   DISPLAY "BINARY-SHORT:
                             " Len-BINARY-SHORT
                             " Len-COMP-1
   DISPLAY "COMP-1:
   DISPLAY "COMP-2:
                             " Len-COMP-2
   DISPLAY "FLOAT-DECIMAL-16: " Len-FLOAT-DECIMAL-16
   DISPLAY "FLOAT-DECIMAL-34: " Len-FLOAT-DECIMAL-34
   DISPLAY "FLOAT-LONG: " Len-FLOAT-LONG
   DISPLAY "FLOAT-SHORT:
                            " Len-FLOAT-SHORT
   DISPLAY "POINTER:
                            " Len-POINTER
   DISPLAY "PROGRAM-POINTER: " Len-PROGRAM-POINTER
   STOP RUN.
```

The output of this program, on a Windows 7 system with a 32-bit MinGW build of Gnu-COBOL is:

```
On this system, with this build of GnuCOBOL, the PICTURE-less USAGE's have these lengths (in bytes):
```

BINARY-C-LONG: 4
BINARY-CHAR: 1
BINARY-DOUBLE: 8
BINARY-LONG: 4

```
BINARY-SHORT: 2
COMP-1: 4
COMP-2: 8
FLOAT-DECIMAL-16: 8
FLOAT-LONG: 8
FLOAT-SHORT: 4
POINTER: 4
PROGRAM-POINTER: 4
```

The output of this program, on a Linux X64 system running cobc (GnuCOBOL) 3.1.2.0 is:

On this system, with this build of GnuCOBOL, the PICTURE-less USAGE's have these lengths (in bytes):

BINARY-C-LONG: 8
BINARY-CHAR: 1
BINARY-DOUBLE: 8
BINARY-LONG: 4
BINARY-SHORT: 2
COMP-1: 4
COMP-2: 8
FLOAT-DECIMAL-16: 8
FLOAT-DECIMAL-34: 16
FLOAT-LONG: 8
FLOAT-SHORT: 4
POINTER: 8
PROGRAM-POINTER: 8

Spot the differences between 32 and 64 bit.

### 6.8.2. 66-Level Data Items

```
66-Level-Data-Item Syntax

66 identifier-1 RENAMES identifier-2 [ THRU|THROUGH identifier-3 ] .
```

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE A 66-level data item regroups previously defined items by specifying alternative, possibly

A 66-level data item regroups previously defined items by specifying alternative, possibly overlapping, groupings of elementary data items.

- 1. The reserved words THRU and THROUGH are interchangeable.
- 2. A level-66 data item cannot rename a level-66, level-01, level-77, or level-88 data item.
- 3. There may be multiple level-66 data items that rename data items contained within the same 01-level record description.
- 4. All RENAMES entries associated with one logical record must immediately follow that record's last data description entry.

### 6.8.3. 77-Level Data Items

### 77-Level-Data-Item Syntax

```
77 identifier-1 [ IS GLOBAL|EXTERNAL ]

[ BASED ]

[ BLANK WHEN ZERO ]

[ JUSTIFIED RIGHT ]

[ PICTURE IS picture-string ]

[ REDEFINES identifier-5 ]

[ SIGN IS LEADING|TRAILING [ SEPARATE CHARACTER ] ]

[ SYNCRONIZED|SYNCHRONISED [ LEFT|RIGHT ] ]

[ USAGE IS data-item-usage ]

[ VALUE IS [ ALL ] literal-1 ] .
```

The LEFT and RIGHT (SYNCRONIZED) clauses are syntactically recognized but are otherwise non-functional.

This syntax is valid in the following sections: WORKING-STORAGE, LOCAL-STORAGE, LINKAGE. The intent of a 77-level item is to be able to create a stand-alone elementary data item.

- 1. The reserved words CHARACTER, IS, RIGHT (JUSTIFIED) and WHEN are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved word JUSTIFIED may be abbreviated as JUST, the reserved word PICTURE may be abbreviated as PIC and the reserved words SYNCRONIZED and SYNCHRONISED may be abbreviated as SYNC.
- 3. New programs requiring a stand-alone elementary item should be coded to use a level number of 01 rather than 77.
- 4. See [Data Description Clauses], page 140, for information on the usage of the various data description clauses.

### 6.8.4. 78-Level Data Items

### 78-Level-Constant Syntax

78 constant-name-1 VALUE IS literal-1 .

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE, SCREEN

The 78-level constant is one of four types of compilation-time constants that can be declared within a program. The other three types are >>DEFINE CDF directive (see [>>DEFINE], page 63) constants, >>SET CDF directive (see [>>SET], page 66) constants and 01-level constants (see [01-Level Constants], page 133).

- 1. The reserved word IS is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. Constants defined in this way become undefined once an END PROGRAM or END FUNCTION is encountered in the input source.
- 3. Data descriptions of this form do not actually allocate any storage they merely define a name (constant-name-1) that may be used anywhere a literal of the same type as literal-1 may be used.
- 4. The constant-name-1 name may not be referenced on a CDF directive.
- 5. Care must be taken that *constant-name-1* does not duplicate any other data item name that has been defined in the program as references to that data item name will refer to the constant and not the data item. The GnuCOBOL compiler will not issue a warning about this condition.

### 6.8.5. 88-Level Data Items

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE, REPORT, SCREEN

Condition names are Boolean (i.e. TRUE / FALSE) data items that receive their TRUE and FALSE values based upon the values of the non 88-level data item whose definition they immediately follow.

- 1. The reserved words ARE, IS, SET and TO are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved words THRU and THROUGH are interchangeable.
- 3. Condition names are always defined subordinate to another (non 88-level) data item. That data item must be an elementary item. Whenever the parent data item assumes one of the values specified on the 88-level item's VALUE (see [VALUE], page 207) clause, conditionname-1 will take on the value of TRUE.
- 4. Condition names do not occupy any storage.
- 5. The optional THROUGH clause allows a range of possible TRUE values to be specified.
- 6. Whenever the parent data item assumes any value *except* one of the values specified on *condition-name-1*'s VALUE clause, *condition-name-1* will take on the value of FALSE.
- 7. Executing the statement SET condition-name-1 TO TRUE will cause condition-name-1's parent data item to take on the first value specified on condition-name-1's VALUE clause.
- 8. Executing the statement SET condition-name-1 TO FALSE will cause condition-name-1's parent data item to take on the value specified on condition-name-1's FALSE clause. If condition-name-1 does not have a FALSE clause, the SET (see [SET], page 330) statement will generate an error message at compilation time.
- 9. See [Condition Names], page 41, for more information.

### 6.9. Data Description Clauses

### 6.9.1. ANY LENGTH

		ANY LENGTH Attribute Syntax	
ANY	LENGTH		
~~~	~~~~		

This syntax is valid in the following sections: LINKAGE

Data items declared with the ANY LENGTH attribute have no fixed compile-time length. Such items may only be defined in the linkage section of a subprogram as they may only serve as subroutine argument descriptions. These items must have a PICTURE (see [PICTURE], page 176) clause that specifies exactly one A, X or 9 symbol.

1. The ANY LENGTH and BASED (see [BASED], page 145) clauses cannot be used together in the same data item description.

6.9.2. AUTO

	AUTO Attribute Syntax
AUTO	

This syntax is valid in the following sections: SCREEN

A field whose description includes this attribute will cause the cursor to automatically advance to the next input-enabled field of a screen if the field is completely filled with input data.

1. The AUTO, AUTO-SKIP (see [AUTO-SKIP], page 142) and AUTOTERMINATE (see [AUTOTERMINATE], page 143) clauses are interchangeable, and may not be used together in the same data item description.

6.9.3. AUTO-SKIP

	AUTO-SKIP Attribute Syntax	
AUTO-SKIP		

This syntax is valid in the following sections: SCREEN

A field whose description includes this attribute will cause the cursor to automatically advance to the next input-enabled field of a screen if the field is completely filled with input data.

1. The AUTO (see [AUTO], page 141), AUTO-SKIP and AUTOTERMINATE (see [AUTOTERMINATE], page 143) clauses are interchangeable, and may not be used together in the same data item description.

6.9.4. AUTOTERMINATE

	AUTOTERMINATE Attribute Syntax	
AUTOTERMINATE		

This syntax is valid in the following sections: SCREEN

A field whose description includes this attribute will cause the cursor to automatically advance to the next input-enabled field of a screen if the field is completely filled with input data.

1. The AUTO (see [AUTO], page 141), AUTO-SKIP (see [AUTO-SKIP], page 142) and AUTOTERMINATE clauses are interchangeable, and may not be used together in the same data item description.

6.9.5. BACKGROUND-COLOR

BACKGROUND-COLOR Attribute Syntax

BACKGROUND-COLOR|BACKGROUND-COLOUR IS integer-1 | identifier-1

This syntax is valid in the following sections: SCREEN

This clause is used to specify the screen background color of the screen data item or the default screen background color of subordinate items if used on a group item.

- 1. The reserved word IS is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. The reserved words ${\tt BACKGROUND-COLOR}$ and ${\tt BACKGROUND-COLOUR}$ are interchangeable.
- 3. You specify colors by number (0-7), or by using the constant names provided in the screenio.cpy copybook (provided with all GnuCOBOL source distributions).
- 4. Colors may also be specified using a numeric non-edited identifier whose value is in the range 0-7.

For composite DISPLAY's, the attributes are always only applied to the previous source-item but the following also allows a change by variable or literal *i.e.*

DISPLAY "Name: " BACKGROUND-COLOR COB-YELLOW NAME-VAR BACKGROUND-COLOR COB-BLACK

END-DISPLAY

See [Color Palette and Video Attributes], page 20, for more information on screen colors and video attributes.

6.9.6. BASED

	BASED Attribute Syntax	
BASED		
~~~~		

This syntax is valid in the following sections: WORKING-STORAGE, LOCAL-STORAGE, LINKAGE

Data items declared with BASED are allocated no storage at compilation time. At run-time, the ALLOCATE (see [ALLOCATE], page 250) or SET ADDRESS (see [SET ADDRESS], page 332) statements are used to allocate space for and (optionally) initialize such items.

- 1. The BASED and ANY LENGTH (see [ANY LENGTH], page 140) clauses cannot be used together in the same data item description.
- 2. The BASED clause may only be used on level 01 and level 77 data items.

### 6.9.7. BEEP

	BEEP Attribute Syntax	
BEEP		

This syntax is valid in the following sections: SCREEN

- 1. The BEEP and BELL (see [BELL], page 147) clauses are interchangeable, and may not be used together in the same data item description.
- 2. Use this clause to cause an audible tone to occur when the screen item is DISPLAYed.

### 6.9.8. BELL

	BELL Attribute Syntax	
BELL		

This syntax is valid in the following sections: SCREEN

- 1. The BEEP (see [BEEP], page 146) and BELL clauses are interchangeable, and may not be used together in the same data item description.
- 2. Use this clause to cause an audible tone to occur when the screen item is DISPLAYed.

### 6.9.9. BLANK

### BLANK Attribute Syntax BLANK LINE|SCREEN

This syntax is valid in the following sections: SCREEN

This clause will blank out either the entire screen (BLANK SCREEN) or just the line upon which data is about to be displayed (BLANK LINE).

- 1. Blanked-out areas will have their foreground and background colors set to the attributes of the field containing the BLANK clause.
- 2. This clause is useful when one screen section item is being displayed over the top of a previously-displayed one.

### 6.9.10. BLANK WHEN ZERO

## BLANK WHEN ZERO

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE, REPORT, SCREEN

This clause will cause that item's value to be automatically transformed into spaces if a value of 0 is ever MOVEd to the item.

- 1. The reserved word WHEN is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. This clause may only be used on a PIC 9 data item with a USAGE (see [USAGE], page 198) of DISPLAY.

### 6.9.11. BLINK

	BLINK Attribute Syntax	
BLINK		

This syntax is valid in the following sections: SCREEN

The BLINK clause modifies the visual appearance of the displayed field by making the field contents blink.

See [Color Palette and Video Attributes], page 20, for more information on screen colors and video attributes.

### 6.9.12. COLUMN

# COLUMN (REPORT SECTION) Clause Syntax COLUMN [ { NUMBER IS } ] [ + | PLUS ] integer-1 ] ~~~ { NUMBERS ARE } COLUMN (SCREEN SECTION) Clause Syntax COLUMN NUMBER IS [ + | PLUS ] integer-2 | identifier-3 ]

This syntax is valid in the following sections: REPORT, SCREEN

The COLUMN clause provides the means of stating in which column a field should be presented on the console window (screen section) or a report (report section).

- 1. The reserved words ARE, IS, NUMBER and NUMBERS are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved word COLUMN may be abbreviated as COL.
- 3. The line location of a report section or screen section field will be determined by the LINE (see [LINE], page 167) clause.
- 4. The value of integer-1 must be 1 or greater.
- 5. If identifier-1 is used to specify either an absolute or relative column position, identifier-1 must be defined as a numeric item of any USAGE (see [USAGE], page 198) other than COMPUTATIONAL-1 or COMPUTATIONAL-2, without editing symbols. The value of identifier-1 at the time the screen data item is presented must be 1 or greater. Note that a COMPUTATIONAL-1 or COMPUTATIONAL-2 identifier will be accepted by the compiler, but will produce unpredictable results at run-time.
- 6. The column coordinate of a field may be stated on an absolute basis (i.e. COLUMN 5) or on a relative basis based upon the end of the previously-presented field (i.e. COLUMN PLUS 1).
- 7. The symbol '+' may be used in lieu of the word PLUS, if desired; if symbol '+' is used, however, there must be at least one space separating it from *integer-1*. Failure to include this space will cause the symbol '+' sign to be simply treated as part of *integer-1* and will treat the COLUMN clause as an absolute column specification rather than a relative one.
- 8. Using relative column positioning (COLUMN PLUS) has slightly different behaviour depending upon the section in which the clause is used, as follows:
  - A. When used on a report section data item, COLUMN PLUS will position the start of the new field's value such that there are *integer-1* blank columns between the end of the previous field and the beginning of this field.
    - If a report data item's description includes the SOURCE (see [SOURCE], page 191), SUM (see [SUM], page 450) or VALUE (see [VALUE], page 207) clause but has no COLUMN clause, COLUMN PLUS 1 will be assumed.
  - B. When used on a screen section data item, COLUMN PLUS will position the new field so that it begins exactly *integer-1* or *identifier-1* characters past the *last* character of the previous field. Thus, COLUMN PLUS 1 will leave no blank positions between the end of the previous field and the start of this one.

If a screen data item's description includes the FROM (see [FROM], page 159), TO (see [TO], page 195), USING (see [USING], page 206) or VALUE (see [VALUE], page 207) clause but has no COLUMN clause, the new screen field will begin at the column coordinate of the last character of the previous field.

### 6.9.13. CONSTANT

	CONSTANT Attribute Syntax	
CONSTANT		

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE, SCREEN

This option signifies that the 01-level data item in whose declaration CONSTANT is specified will be treated as a symbolic name for a literal value, usable wherever a literal of the appropriate type could be used.

- 1. The value of a data item defined as a constant cannot be changed at run-time. In fact, it is not syntactically acceptable to use such a data item as the destination field of any procedure division statement that stores a value.
- 2. See [01-Level Constants], page 133, for additional information.

### **6.9.14.** EMPTY-CHECK

	EMPTY-CHECK Attribute Syntax
EMPTY-CHECK	

This syntax is valid in the following sections: SCREEN

This clause forces the user to enter data into the field it is specified on (or into all subordinate input-capable fields if EMPTY-CHECK is specified on a group item).

- 1. The EMPTY-CHECK and REQUIRED (see [REQUIRED], page 187) clauses are interchangeable, and may not be used together in the same data item description.
- 2. In order to take effect, the user must first move the cursor into the field having this clause in its definition.
- 3. The ACCEPT data-item statement (see [ACCEPT data-item], page 234) will ignore the Enter key and any other cursor-moving keystrokes that would cause the cursor to move to another screen item *unless* data has been entered into the field. Function keys will still be allowed to terminate the ACCEPT.
- 4. In order to be functional, this attribute must be supported by the underlying "curses" package your GnuCOBOL implementation was built with. As of this time, the "PDCurses" package (used for native Windows or MinGW builds) does not support EMPTY-CHECK.

### 6.9.15. ERASE

	ERASE Clause Syntax
ERASE EOL EOS	

This syntax is valid in the following sections: SCREEN

ERASE will blank-out screen contents from the location where the screen data item whose description contains this clause will be displayed, forward until the end of the screen (ERASE EOS)

- 1. Erased areas will have their foreground and background colors set to the attributes of the field containing the ERASE clause.
- 2. This clause is useful when one screen section item is being displayed over the top of a previously-displayed one.

See [Color Palette and Video Attributes], page 20, for more information on screen colors and video attributes.

### 6.9.16. EXTERNAL

	EXTERNAL Attribute Syntax
EXTERNAL	

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE

This clause marks a data item description, FD or SD see [File/Sort-Description], page 113, as being shareable with other programs executed from the same execution thread.

- 1. By specifying the EXTERNAL clause on either an FD or an SD, the file description is capable of being shared between all programs executed from the same execution thread, provided an EXTERNAL clause is coded with the file's description in *each* program requiring it. This sharing allows the file to be opened, read and/or written and closed in different programs. This sharing applies to the record descriptions subordinate to the file description too.
- 2. By specifying the EXTERNAL clause on the description of a data item, the data item is capable of being shared between all programs executed from the same execution thread, provided the data item is coded (with an EXTERNAL clause) in each program requiring it.
- 3. The following points apply to the specification of EXTERNAL in a data item's definition:
  - A. The EXTERNAL clause may only be specified at the 77 or 01 level.
  - B. An EXTERNAL item must have a data name and that name cannot be FILLER.
  - C. EXTERNAL cannot be combined with BASED (see [BASED], page 145), GLOBAL (see [GLOBAL], page 161) or REDEFINES (see [REDEFINES], page 185).

### 6.9.17. FALSE

LINKAGE, REPORT, SCREEN

### **FALSE Clause Syntax**

WHEN SET TO FALSE IS literal-1

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE,

This clause, which may only appear on the definition of a level-88 condition name, is used to specify the value of the data item that serves as the parent of the level-88 condition name that will force the condition name to assume a value of FALSE.

- 1. The reserved words IS, SET, TO and WHEN are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. See [88-Level Data Items], page 139, or See [Condition Names], page 41, for more information.

### 6.9.18. FOREGROUND-COLOR

### FOREGROUND-COLOR Attribute Syntax

FOREGROUND-COLOR|FOREGROUND-COLOUR IS integer-1 | identifier-1

This syntax is valid in the following sections: SCREEN

This clause is used to specify the color of text within a screen data item or the default text color of subordinate items if used on a group item.

- 1. The reserved word IS is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. The reserved words FOREGROUND-COLOR and FOREGROUND-COLOUR are interchangeable.
- 3. You specify colors by number (0-7), or by using the constant names provided in the screenio.cpy copybook (which is provided with all GnuCOBOL source distributions).
- 4. Colors may also be specified using a numeric non-edited identifier whose value is in the range 0-7.

See [Color Palette and Video Attributes], page 20, for more information on screen colors and video attributes.

### 6.9.19. FROM

### FROM Clause Syntax

FROM literal-1 | identifier-5

This syntax is valid in the following sections: SCREEN

This clause is used to specify either the data item a screen section field is to obtain its value from when the screen is displayed, or a literal that will specify the value of that same field.

1. The FROM, TO (see [TO], page 195), USING (see [USING], page 206) and VALUE (see [VALUE], page 207) clauses are mutually-exclusive in any screen section data item's definition.

### 6.9.20. FULL

	FULL Attribute Syntax
FULL	

This syntax is valid in the following sections: SCREEN

The FULL clause forces the user to enter data into the field it is specified on (or into all subordinate input-capable fields if specified on a group item) sufficient to fill every character position of the field.

- 1. The FULL and LENGTH-CHECK (see [LENGTH-CHECK], page 166) clauses are interchangeable, and may not be used together in the same data item description.
- 2. In order for this clause to take effect at execution time, the user must move the cursor into the field having this clause in its definition.
- 3. The ACCEPT data-item statement (see [ACCEPT data-item], page 234) will ignore the Enter key and any other cursor-moving keystrokes that would cause the cursor to move to another screen item unless the proper amount of data has been entered into the field. Function keys will still be allowed to terminate the ACCEPT, however.
- 4. In order to be functional, this attribute must be supported by the underlying "curses" package your GnuCOBOL implementation was built with. As of this time, the "PDCurses" package (used for native Windows or MinGW builds) does not support FULL.

### 6.9.21. GLOBAL

	GLOBAL Attribute Syntax	
GLOBAL		

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, REPORT This clause marks a data item, 01-level constant, FD (see [File/Sort-Description], page 113), SD (see [File/Sort-Description], page 113) or an RD (see [REPORT SECTION], page 124) as being shareable with any nested subprograms.

- 1. By specifying the GLOBAL clause on the description of a file or a report, that description is capable of being shared between a program and any nested subprograms within it, provided the FD, SD or RD is coded (with a GLOBAL clause) in each nested subprogram requiring it. This sharing allows the file to be opened, read and/or written and closed or the report to be initiated or terminated in those programs. Separately compiled programs may not share a GLOBAL file description, but they may share an EXTERNAL (see [EXTERNAL], page 156) file description. This sharing applies to the record descriptions subordinate to the file description and the report groups subordinate to the RD also.
- 2. By specifying the GLOBAL clause on the description of a data item, the data item is capable of being shared between a program and any nested subprograms within it, provided the data item is coded (with a GLOBAL clause) in each program requiring it.
- 3. The following points apply to the specification of GLOBAL in a data item's definition:
  - A. The GLOBAL clause may only be specified at the 77 or 01 level.
  - B. A GLOBAL item must have a data name and that name cannot be FILLER.
  - C. GLOBAL cannot be combined with EXTERNAL (see [EXTERNAL], page 156), REDEFINES (see [REDEFINES], page 185) or BASED (see [BASED], page 145).

### 6.9.22. GROUP INDICATE

## GROUP-INDICATE Attribute Syntax GROUP INDICATE

This syntax is valid in the following sections: REPORT

The GROUP INDICATE clause specifies that the data item in whose definition the clause appears will be presented only in very limited circumstances.

- 1. This clause may only appear within a DETAIL report group (see [TYPE], page 196).
- 2. When this clause is present, the data item in question will be presented only under the following circumstances:
  - A. On the first presentation of the detail group following the INITIATE (see [INITIATE], page 296) of the report.
  - B. On the first presentation of the detail group after every new page is started.
  - C. On the first presentation of the detail group after any control break occurs.

### 6.9.23. HIGHLIGHT

	HIGHLIGHT Attribute Syntax
HIGHLIGHT	

This syntax is valid in the following sections: SCREEN

This clause controls the intensity of text (FOREGROUND-COLOR (see [FOREGROUND-COLOR], page 158)) by setting that intensity to its highest of three possible settings.

1. This clause, along with LOWLIGHT (see [LOWLIGHT], page 169), are intended to provide a three-level intensity scheme (LOWLIGHT . . . nothing (Normal) . . . HIGHLIGHT).

See [Color Palette and Video Attributes], page 20, for more information on screen colors and video attributes.

### 6.9.24. JUSTIFIED

### JUSTIFIED Attribute Syntax

JUSTIFIED RIGHT

~ ~ ~ ~

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE, REPORT, SCREEN

The presence of a JUSTIFIED RIGHT clause in a data item's definition alters the manner in which data is stored into the field from the default 'left-justified, space filled' behaviour to 'right justified, space filled'.

- 1. The reserved word RIGHT is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. The reserved word JUSTIFIED may be abbreviated as JUST.
- 3. This clause is valid only on alphabetic (PIC A) or alphanumeric (PIC X) data items.
- 4. The presence or absence of this clause influences the behaviour of the MOVE (see [MOVE], page 305) statement as well as the FROM (see [FROM], page 159), SOURCE (see [SOURCE], page 191) and USING (see [USING], page 206) data item description clauses.
- 5. If the value being stored into the field is the same length as the receiving field, the presence or absence of the JUSTIFIED RIGHT clause on that field's description is irrelevant.
- 6. The following examples illustrate the behaviour of the presence and absence of the JUSTIFIED RIGHT clause when the field size is different than that of the value being stored. In these examples, the symbol b represents a space.

When the value is *shorter* than the field size:

Without JUSTIFIED With JUSTIFIED

01 A PIC X(6). 01 A PIC X(6) JUSTIFIED RIGHT.

MOVE @code{ABC} TO A MOVE @code{ABC} TO A

Result Result bbbABC

When the value is *longer* than the field size:

Without JUSTIFIED With JUSTIFIED

O1 A PIC X(6). O1 A PIC X(6) JUSTIFIED RIGHT.

MOVE 'ABCDEFGHI' TO A MOVE 'ABCDEFGHI' TO A

Result Result ABCDEF DEFGHI

### 6.9.25. LEFTLINE

	LEFTLINE Attribute Syntax
LEFTLINE	

This syntax is valid in the following sections: SCREEN

The LEFTLINE clause will introduce a vertical line at the left edge of a screen field.

- 1. The LEFTLINE, OVERLINE (see [OVERLINE], page 175) and UNDERLINE (see [UNDERLINE], page 197) clauses may be used in any combination in a single field's description.
- 2. This clause is essentially non-functional when used within Windows command shell (cmd.exe) environments and running programs compiled using a GnuCOBOL implementation built using "PDCurses" (such as Windows/MinGW builds).
- 3. Whether or not this clause operates on Cygwin or UNIX/Linux/OSX systems will depend upon the video attribute capabilities of the terminal output drivers and "curses" software being used.

See [Color Palette and Video Attributes], page 20, for more information on screen colors and video attributes.

### 6.9.26. LENGTH-CHECK

	LENGTH-CHECK Attribute Syntax
LENGTH-CHECK	

This syntax is valid in the following sections: SCREEN

The LENGTH-CHECK clause forces the user to enter data into the field it is specified on (or into all subordinate input-capable fields if specified on a group item) sufficient to fill every character position of the field.

- 1. The FULL (see [FULL], page 160) and LENGTH-CHECK clauses are interchangeable, and may not be used together in the same data item description.
- 2. In order for this clause to take effect at execution time, the user must move the cursor into the field having this clause in its definition.
- 3. The ACCEPT data-item statement (see [ACCEPT data-item], page 234) will ignore the Enter key and any other cursor-moving keystrokes that would cause the cursor to move to another screen item unless the proper amount of data has been entered into the field. Function keys will still be allowed to terminate the ACCEPT, however.
- 4. In order to be functional, this attribute must be supported by the underlying "curses" package your GnuCOBOL implementation was built with. As of this time, the "PDCurses" package (used for native Windows or MinGW builds) does not support LENGTH-CHECK.

#### 6.9.27. LINE

#### LINE (REPORT SECTION) Clause Syntax

#### LINE (SCREEN SECTION) Clause Syntax

```
[ LINE NUMBER IS [ +|PLUS ] integer-4 | identifier-6 ]
```

This syntax is valid in the following sections: REPORT, SCREEN

This clause provides a means of explicitly stating on which line a field should be presented on the console window (screen section) or on a report (report section).

- 1. The reserved words IS, NUMBER and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The following points document the use of format 1 of the LINE clause:
  - A. The column location of a report item will be determined by the COLUMN (see [COLUMN], page 151) clause.
  - B. The value of integer-1 must be 1 or greater.
  - C. The report line number upon which the data item containing this clause along with any subordinate data items will be presented may be stated on an absolute basis (*i.e.* LINE 5) or on a relative basis based upon the previously-displayed line (*i.e.* LINE PLUS 1).
  - D. The symbol '+' may be used in lieu of the word PLUS, if desired; if '+' is used, however, there must be at least one space separating it from *integer-1*. Failure to include this space will cause the '+' to be simply treated as part of *integer-1* and will treat the LINE clause as an absolute line specification rather than a relative one.
  - E. The optional NEXT PAGE clause specifies that regardless of whether or not the report group containing this clause *could* fit on the report page being currently generated, the report group will be *forced* to appear on a new page.
- 3. The following points document the use for format 2 of the LINE clause:
  - A. The column location of a screen section field is determined by the COLUMN (see [COLUMN], page 151) clause.
  - B. The value of integer-1 must be 1 or greater.
  - C. If identifier-1 is used to specify either an absolute or relative column position, identifier-1 must be defined as a numeric item of any USAGE (see [USAGE], page 198) other than COMPUTATIONAL-1 or COMPUTATIONAL-2, without editing symbols. The value of identifier-1 at the time the screen data item is presented must be 1 or greater. Note that

- a COMPUTATIONAL-1 or COMPUTATIONAL-2 identifier will be accepted by the compiler, but will produce unpredictable results at run-time.
- D. The screen line number upon which the data item containing this clause along with any subordinate data items will be displayed may be stated on an absolute basis (*i.e.* LINE 5) or on a relative basis based upon the previously-displayed line (*i.e.* LINE PLUS 1).
- E. The symbol '+' may be used in lieu of the word PLUS, if desired; if '+' is used, however, there must be at least one space separating it from *integer-1*. Failure to include this space will cause the '+' to be simply treated as part of *integer-1* and will treat the LINE clause as an absolute line specification rather than a relative one.
- F. If a screen data item's description includes the FROM (see [FROM], page 159), TO (see [TO], page 195), USING (see [USING], page 206) or VALUE (see [VALUE], page 207) clause but has no LINE clause, the "current screen line" will be assumed.

#### 6.9.28. LOWLIGHT

	LOWLIGHT Attribute Syntax	
LOWLIGHT		

This syntax is valid in the following sections: SCREEN

The LOWLIGHT clause controls the intensity of text (FOREGROUND-COLOR) by setting that intensity to its lowest of three possible settings.

1. This clause, along with HIGHLIGHT (see [HIGHLIGHT], page 163), are intended to provide a three-level intensity scheme (LOWLIGHT . . . nothing (Normal) . . . HIGHLIGHT). In environments such as a Windows console where only two levels of intensity are supported, LOWLIGHT is the same as leaving this clause off altogether.

#### 6.9.29. NEXT GROUP

# NEXT GROUP IS { [ +|PLUS ] integer-2 } """ } { NEXT | NEXT | NEXT | PAGE | PAGE }

This syntax is valid in the following sections: REPORT

This clause defines any rules for where the next group to be presented on a report will begin, line-wise, with respect to the *last* line of the group in which this clause appears.

- 1. The reserved word IS is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. The terms NEXT, NEXT PAGE and PAGE are interchangeable.
- 3. A report group must contain at least one LINE NUMBER clause in order to also contain a NEXT GROUP clause.
- 4. If the RD (see [REPORT SECTION], page 124) in which the report group containing a NEXT GROUP clause does not contain a PAGE LIMITS clause, only the PLUS integer-1 option may be specified.
- 5. The NEXT PAGE option cannot be used in a PAGE FOOTING.
- 6. The NEXT GROUP option cannot be specified in either a REPORT HEADING or a PAGE HEADING.
- 7. The effects of NEXT GROUP will be in addition to any line spacing defined by the next-presented group's LINE NUMBER clause.

#### 6.9.30. NO-ECHO

	NO-ECHO Attribute Syntax
NO-ECHO	

This syntax is valid in the following sections: SCREEN

The NO-ECHO clause will cause all data entered into the field to appear on the screen as asterisks.

- 1. The NO-ECHO and SECURE (see [SECURE], page 189) clauses are interchangeable, and may not be used together in the same data item description.
- 2. This clause may only be used on a field allowing data entry (a field containing either the USING (see [USING], page 206) or TO (see [TO], page 195) clause).

#### 6.9.31. OCCURS

#### **OCCURS Clause Syntax**

```
GENERAL FORMAT.
Format 1 (fixed-table):
 OCCURS integer-2 TIMES
 ~~~~~
Format 2 (occurs-depending-table):
OCCURS [integer-1 TO] { integer-2 TIMES } [DEPENDING ON identifier-1]
 ~~ { UNBOUNDED } ~~~~~~
 [ASCENDING|DESCENDING KEY IS identifier-5 ...] ...
 [INDEXED BY index-name-1 ...]
REPORT SECTION.
Format 3
OCCURS [integer-1 TO] integer-2 TIMES [DEPENDING ON identifier-1]
 [STEP integer-3]
 [VARYING identifier-2 FROM { identifier-3 } BY { identifier-4 }]
                         ~~~~ { integer-4 } ~~ { integer-5
SCREEN SECTION.
Format 4
OCCURS integer-2 TIMES
```

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE, REPORT, SCREEN

The <code>OCCURS</code> clause is used to create a data structure called a table, where entries in that structure repeat multiple times.

1. The reserved words BY (INDEXED), IS, KEY, ON and TIMES are optional and may be omitted. The presence or absence of these words has no effect upon the program.

- 2. The value of integer-2 specifies how many entries will be allocated in the table.
- 3. The following is an example of how a table might be defined:

```
05 QUARTERLY-REVENUE OCCURS 4 TIMES PIC 9(7) V99.
```

This will allocate the following:

```
QUARTERLY-REVENUE (1)
QUARTERLY-REVENUE (2)
QUARTERLY-REVENUE (3)
QUARTERLY-REVENUE (4)
```

Each occurrence is referenced using the subscript syntax (a numeric literal, arithmetic expression or numeric identifier enclosed within parenthesis) shown above.

4. The OCCURS clause may be used at the group level too, in which case the entire group structure repeats, as follows:

```
05 GRP OCCURS 3 TIMES.

10 A PIC X(1).

10 B PIC X(1).

10 C PIC X(1).
```

This would allow references to any of the following:

```
\mathtt{GRP}(1) includes A(1), B(1) and C(1) \mathtt{GRP}(2) includes A(2), B(2) and C(2) \mathtt{GRP}(3) includes A(3), B(3) and C(3)
```

or each A,B,C item could be referenced as follows:

```
A(1)
        character #1 of GRP(1)
B(1)
        character #2 of GRP(1)
C(1)
        character #3 of GRP(1)
A(2)
        character #1 of GRP(2)
B(2)
        character #2 of GRP(2)
C(2)
        character #3 of GRP(2)
A(3)
        character #1 of GRP(3)
B(3)
        character #2 of GRP(3)
C(3)
        character #3 of GRP(3)
```

- 5. The optional DEPENDING ON clause can be added to an OCCURS to create a variable-length table. In such cases, the value of *integer-1* specifies what the minimum number of entries in the table will be while *integer-2* specifies the maximum. Such tables will be allocated out to the maximum size specified as *integer-2*. At execution time the value of *identifier-1* will determine how many of the table elements are accessible.
- 6. See the documentation of the SEARCH (see [SEARCH], page 327), SEARCH ALL (see [SEARCH ALL], page 328) and SORT (see [SORT], page 339) statements for explanations of the KEY and INDEXED BY clauses.
- 7. The OCCURS clause cannot be specified in a data description entry that has a level number of 01, 66, 77, or 88, although it is valid in data items described *subordinate* to an 01-level data item.
- 8. The following points apply to an OCCURS used in the report section:
  - A. The optional STEP clause defines an incrementation value that will be added to any absolute LINE (see [LINE], page 167) or COLUMN (see [COLUMN], page 151) number specifications that may be part of or subordinate to this data item's definition.
  - B. The optional VARYING clause defines an identifier that may be used as a subscript for the multiple occurrences of this or any subordinate data item should the SOURCE (see

- [SOURCE], page 191) or SUM (see [SUM], page 450) clause(s) on this or subordinate data items reference entries within the table. The *identifier-2* data item is dynamically created as needed and cannot be referenced outside the scope of the report data item definition.
- C. The following two examples illustrate two different ways a report could include four quarters worth of sales figures in its detail lines one doing things 'the hard way' and one using the advanced OCCURS capabilities of STEP and VARYING. Both assume the definition of the following table exists in working-storage:

05 SALES OCCURS 4 TIMES PIC 9(7)V99.

First, the "Hard Way":

```
10 COL 7 PIC $(7)9.99 SOURCE SALES(1).
```

10 COL 17 PIC \$(7)9.99 SOURCE SALES(2).

10 COL 27 PIC \$(7)9.99 SOURCE SALES(3).

10 COL 37 PIC \$(7)9.99 SOURCE SALES(4).

And then using STEP and VARYING:

10 COL 7 OCCURS 4 TIMES STEP 10 VARYING QTR FROM 1 BY 1 PIC \$(7)9.99 SOURCE SALES(QTR).

#### **6.9.32. OVERLINE**

OVERLINE Attribute Syntax			
OVERLINE			

This syntax is valid in the following sections: SCREEN

The OVERLINE clause will introduce a horizontal line at the top edge of a screen field.

- 1. The LEFTLINE (see [LEFTLINE], page 165), OVERLINE and UNDERLINE (see [UNDERLINE], page 197) clauses may be used in any combination in a single field's description.
- 2. This clause is essentially non-functional when used within Windows command shell (cmd.exe) environments and running programs compiled using a GnuCOBOL implementation built using "PDCurses" (such as Windows/MinGW builds).
- 3. Whether or not this clause operates on Cygwin or UNIX/Linux/OSX systems will depend upon the video attribute capabilities of the terminal output drivers and "curses" software being used.

#### 6.9.33. PICTURE

#### **PICTURE Clause Syntax**

PICTURE IS picture-string

This syntax is valid in the following sections: FILE WORKING_STORAGE LOCAL_STORAGE

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE, REPORT, SCREEN

The picture clause defines the class (numeric, alphabetic or alphanumeric), size and format of the data that may be contained by the data item being defined. Sometimes this role is assisted by the USAGE (see [USAGE], page 198) clause, and in a few instances will be assumed entirely by that clause.

- 1. The reserved word IS is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. The reserved word PICTURE may be abbreviated as PIC. Most programmers prefer to use the latter.
- 3. A picture clause may only be specified on an elementary item.
- 4. A picture-string is a sequence of the special symbols '\$', '*', '+', ',', '-', '.', '/', '0' (zero), '9', 'A', 'B', CR, DB, 'S', 'V', 'X' and 'Z'.
- 5. In general, each picture symbol represents either a single character in storage or a single decimal digit. There are a few exceptions, and they will be discussed as needed.
- 6. When a picture-string contains a repeated sequence of symbols PIC 9999/99/99 for example, the repetition can be specified using a parenthetic repeat count, as in PIC 9(4)/9(2)/9(2). Using repeat counts is optional and their use (or not) is entirely at the discretion of the programmer. Many programmers use repetition for small sequences (PIC XXX) and repeat counts for larger ones (PIC 9(9).
- 7. This first set of picture symbols defines the basic data type of a data item. Each symbol represents a single character's worth of storage.
  - 'A' Defines storage reserved for a single alphabetic character ('A'-'Z', 'a'-'z').
  - 'N' Defines storage reserved for a single character in the computer's National Character set. Support for national character sets in GnuCOBOL is currently only partially implemented, and the compile- and run-time effect of using the 'N' picture symbol is the same as if X(2) had been coded, with the additional effect that such a field will qualify as a NATIONAL or NATIONAL-EDITED field on an INITIALIZE (see [INITIALIZE], page 292) statement.
  - 'X' Defines storage reserved for a single alphanumeric character (any character).
  - '9' Defines storage reserved for a single numeric digit character ('0'-'9').

Typically, only one kind of each of those symbols is used in the same picture clause, but that isn't a requirement. Data items that, of the three symbols above, use nothing but 'A' picture symbols are known as *Alphabetic Data Items* while those that use '9' picture symbols without any 'A' or 'X' symbols (or those that have a USAGE without a PICTURE) are known as *Numeric Data Items*. All other data items are referred to as *Alphanumeric Data Items*.

If you need to allocate space for a data item whose format is two letters followed by five digits followed by three letters, you could use the *picture-string* AA99999AAA, A(2)9(5)A(3)

XXXXXXXXX or X(10). There is absolutely no functional difference whatsoever between the four — none of them provide any functionality the others do not. The first two probably make for better *documentation* of the expected field contents, but they don't provide any run-time enforcement capabilities.

As far as enforcement goes, however, both alphabetic and numeric picture strings do provide for both compile-time and run-time enforcement capabilities. In the case of compilation enforcement, the compiler can issue warning messages if you attempt to specify a non-numeric value for a numeric data item or if you attempt to MOVE (see [MOVE], page 305) a non-numeric data item to one that is numeric. Similar capabilities exist for alphabetic data items. At run-time, you may use a special class test (see [Class Conditions], page 42) to determine if the contents of a data item are entirely numeric or entirely alphabetic.

8. The following picture symbols may be used with numeric data items.

Defines an implied digit position that will be considered to be a zero when the data item is referenced at run-time. This symbol is used to allow data items that will contain very large values to be allocated using less storage by assuming a certain number of trailing zeros (one per 'P') to exist at the end of values.

The 'P' symbol is not allowed in conjunction with 'N'.

The 'P' symbol may only be used at the beginning or end of a picture clause. 'P' is a repeatable symbol.

All computations and MOVE (see [MOVE], page 305) operations involving such a data item will behave as if the zeros were actually there.

For example, let's say you need to allocate a data item that contains however many millions of dollars of revenue your company has in gross revenues this year:

#### 01 Gross-Revenue PIC 9(9).

In which case 9 characters of storage will be reserved. The values 0000000000 through 99999999 will represent the gross-revenues. But, if only the millions are tracked (meaning the last six digits are always going to be 0), you could define the field as:

#### 01 Gross-Revenue PIC 9(3)P(6).

Whenever Gross-Revenue is referenced in calculations, or whenever its value is moved to another data item, the value of Gross-Revenue will be treated as if it is nnn000000, where nnn is the actual value in storage.

If you wanted to store the value 128 million into that field, you would do so as if the 'P's were '9's:

#### MOVE 128000000 TO Gross-Revenue

A DISPLAY (see [DISPLAY], page 263) of a data item containing 'P' symbols is a little strange. The value displayed will be what is actually in storage, but the total size of the displayed value will be as if the 'P' symbols had been '9's. Thus, after the above statement established a value for Gross-Revenue, a DISPLAY Gross-Revenue would produce output of '000000128'.

'S' This symbol, if used, must be the very first symbol in the PICTURE value. A 'S' indicates that the data item is Signed, meaning that negative values are possible for this data item. Without an 'S', any negative values stored into this data item via a MOVE or arithmetic statement will have the negative sign stripped from it (in effect becoming the absolute value).

The 'S' symbol is not allowed in conjunction with 'N'.

٠p'

The 'S' symbol may only occur once in a picture string. See [SIGN IS], page 190, for further discussion of how negative values may be stored in a numeric data item.

'V' This symbol is used to define where an implied decimal-point (if any) is located in a numeric item. Just as there may only be a single decimal point in a number so may there be no more than one 'V' in a PICTURE. Implied decimal points occupy no space in storage — they just specify how values are used. For example, if the value 1234 is in storage in a field defined as PIC 999V9, that value would be treated as 123.4 in any statements that referenced it.

The 'V' symbol is not allowed in conjunction with 'N'.

The 'V' symbol may only occur once in a picture string.

- 9. Any editing symbols introduced past this point will, if coded in the picture clause of an otherwise numeric data item, transform that data item from a numeric to a *Numeric Edited* data item. Numeric edited data items are treated as alphanumeric and may not serve either as table subscripts or as source arguments on an arithmetic statement.
- 10. The following are the fixed insertion editing symbols that may be specified in a picture string. Each of these editing symbols will insert a special character into the field value at the position it is specified in the picture string. These editing symbols will each introduce one extra character into the total field size for each occurrence of the symbol in the picture string.
  - 'B' The 'B' editing symbol introduces a blank into the field value for each occurrence.

Multiple 'B' symbols may be coded.

The following example will format a ten digit number (presumably a telephone number) into a '### #### 'layout:

```
..
05 Phone-Number PIC 9(3)B9(3)B9(4).
..
MOVE 5185551212 TO Phone-Number
DISPLAY Phone-Number
```

This code will display '518 555 1212'.

'0' The '0' (zero) editing symbol introduces one "0" character into the field value for each occurrence in the picture string.

Multiple '0' symbols may be coded.

Here's an example:

```
O5 Output-Item PIC 909090909.

MOVE 12345 TO Output-Item
DISPLAY Output-Item
```

The above will display '102030405'.

'/' The '/' editing symbol inserts one "/" character into the field value for each occurrence in the picture string.

Multiple '/' symbols may be coded.

This editing symbol is most-frequently used to format dates, as follows:

. . .

```
05 Year-Month-Day PIC 9(4)/9(2)/9(2).
...
MOVE 20140207 TO Year-Month-Day
DISPLAY Year-Month-Day
```

This example displays '2014/02/07'.

- 11. The following are the numeric formatting symbols that may be specified in a picture string. Each of these editing symbols will insert special characters into the field value to present numbers in a "friendly" format. These editing symbols will each introduce one extra character into the total field size for each occurrence of the symbol in the picture string. Numeric fields whose picture clause contains these characters may neither be used as source fields in any calculation nor may they serve as source fields for the transfer of data values to any data item other than an alphanumeric field.
  - '.' The '.' symbol inserts a decimal point into a numeric field value. When the contents of a numeric data item sending field are moved into a receiving data item whose picture clause contains the '.' editing symbol, implied ('V') or actual decimal point in the sending data item or literal, respectively, will be aligned with the '.' symbol in the receiving field. Digits are then transferred from the sending to the receiving field outward from the sending field's 'V' or '.', truncating sending digits if there aren't enough positions in the receiving field. Any digit positions in the receiving field that don't receive digits from the sending field, if any, will be set to 0.

The '.' symbol is not allowed in conjunction with 'N'.

An example will probably help:

```
...
05 Source-Field PIC 9(2)V9 VALUE 7.2.
05 Dest-Field PIC 9(5).9(2).
...
MOVE 1234567.89 TO Dest-Field
DISPLAY Dest-Field
MOVE 19 TO Dest-Field
DISPLAY Dest-Field
MOVE Source-Field TO Dest-Field
DISPLAY Dest-Field
```

The example will display three results — '34567.89', '00019.00' and '00007.20'.

Both data item definitions *appear* to have *two* decimal points in their picture clauses. They actually don't, because the last character of every data item definition is always a period — the period that ends the definition.

The ',' symbol serves as a thousands separator. Many times, you'll see large numbers formatted with these symbols — for example, 123,456,789. This can be accomplished easily by adding thousands separator symbols to a picture string. Thousands separator symbols that aren't needed will behave as if they were '9's.

The ',' symbol is not allowed in conjunction with 'N'.

Here's an example:

```
...
05 My-Lottery-Winnings PIC 9(3),9(3),9(3)...
```

### MOVE 12345 TO My-Lottery-Winnings DISPLAY My-Lottery-Winnings

The value '0000012,345' (a very disappointing one for my retirement plans, but a good thousands separator demo) will be displayed. Notice how, since the first comma wasn't needed due to the meagre amount I won, it behaved like another '9'.

If desired, you may reverse the roles of the '.' and ',' editing symbols by specifying DECIMAL POINT IS COMMA in the SPECIAL-NAMES (see [SPECIAL-NAMES], page 84) paragraph.

- 12. The following are insertion symbols. They are used to insert an extra character (two in the case of CR and DB) to signify the sign (positive or negative) of the numeric value that is moved into the field whose picture string contains one of these symbols, or the fact that the data item represents a currency (money) amount. Only one of the '+', '-', CR or DB symbols may be used in a picture clause. In this context, when any of these symbols are used in a picture-string, they must be at the end. The '+', '-' and/or currency symbols may also be used as floating editing symbols at the beginning of the picture-string a subject that will be covered in the next numbered paragraph.
  - '+' If the value of the numeric value moved into the field is positive (0 or greater), a '+' character will be inserted. If the value is negative (less than 0), a '-' character is inserted.

The '+' symbol is not allowed in conjunction with 'N'.

'-' If the value of the numeric value moved into the field is positive (0 or greater), a space will be inserted. If the value is negative (less than 0), a '-' character is inserted.

The '-' symbol is not allowed in conjunction with 'N'.

CR This symbol is coded as the two characters 'C' and 'R'. If the value of the numeric value moved into the field is positive (0 or greater), two spaces will be inserted. If the value is negative (less than 0), the characters CR (credit) are inserted.

The CR symbol is not allowed in conjunction with 'N'.

DB This symbol is coded as the two characters 'D' and 'B'. If the value of the numeric value moved into the field is positive (0 or greater), two spaces will be inserted. If the value is negative (less than 0), the characters DB (debit) are inserted.

The DB symbol is not allowed in conjunction with 'N'.

'\$' Regardless of the value moved into the field, this symbol will insert the currency symbol into the data item's value in the position where it occurs in the *picture-string* (see [SPECIAL-NAMES], page 84).

The '\$' symbol is not allowed in conjunction with 'N'.

- 13. These editing symbols are known as floating replacement symbols. These symbols may occur in sequences *before* any '9' editing symbols in the *picture-string* of a numeric data item. Using these symbols transforms that numeric data item into a numerid *edited* data item, which can no longer be used in calculations or subscripts.
- 14. Each of the following symbols behave like a '9', until such point as all digits in the numeric value are exhausted and leading zeros are about to be inserted. In effect, these editing symbols define what should happen to those leading zero.
  - '\$' Of those currency symbols that correspond to character positions in which leading zeros reside, the right-most will have its '0' value replaced by the currency

symbol in-effect for the program (see [SPECIAL-NAMES], page 84). Any remaining leading zero values occupying positions described by this symbol will be replaced by spaces.

The '\$' symbol is not allowed in conjunction with 'N'.

Any currency symbol coded to the right of a '.' will be treated exactly like a '9'.

'*' This symbol is referred to as a check protection symbol. All check-protection symbols that correspond to character positions in which leading zeros reside will have their '0' values replaced by '*'.

The '*' symbol is not allowed in conjunction with 'N'.

Any check-suppression symbol coded to the right of a '.' will be treated exactly like a '9'.

'+' Of those '+' symbols that correspond to character positions in which leading zeros reside, the right-most will have its '0' value replaced by a '+' if the value in the data item is zero or greater or a '-' otherwise. Any remaining leading zero values occupying positions described by this symbol will be replaced by spaces. You cannot use both '+' and '-' in the same picture-string.

The '+' symbol is not allowed in conjunction with 'N'.

Any '+' symbol coded to the right of a '.' will be treated exactly like a '9'.

'-' Of those '-' symbols that correspond to character positions in which leading zeros reside, the right-most will have its '0' value replaced by a space if the value in the data item is zero or greater or a '-' otherwise. Any remaining leading zero values occupying positions described by this symbol will be replaced by spaces. You cannot use both '+' and '-' in the same picture-string.

The '-' symbol is not allowed in conjunction with 'N'.

Any '-' symbol coded to the right of a '.' will be treated exactly like a '9'.

'Z' All 'Z' symbols that correspond to character positions in which leading zeros reside will have their '0' values replaced by spaces.

Any zero-suppression symbol coded to the right of a '.' will be treated exactly like a '9'.

'Z' and '*' should not be coded in the same picture-string

'+' and '-' should not be coded in the same picture-string

When multiple floating symbols are coded, even if there is only one of them used they will all be considered floating and will all be able to assume each other's properties. For example, if a data item has a PIC +\$2ZZZ9.99 picture-string, and a value of 1 is moved to that field at run-time, the resulting value will be (the b symbol represents a space) bbbb+\$1.00. This is not consistent with many other COBOL implementations, where the result would have been +\$bbbb1.00.

Most other COBOL implementations reject the use of multiple occurrences of multiple floating editing symbols. For example, they would reject *picture-strings* such as +++\$\$\$9.99, \$\$\$ZZZ9.99 and so on. GnuCOBOL accepts these. Programmers creating GnuCOBOL programs should avoid such *picture-strings* if there is any likelihood that those programs may be used with other COBOL implementations.

#### 6.9.34. PRESENT WHEN

## PRESENT-WHEN Clause Syntax PRESENT WHEN condition-name

This syntax is valid in the following sections: REPORT

This clause names an existing Condition Name (see [Condition Names], page 41) that will serve as a switch controlling the presentation or suppression of a report group.

- 1. If the specified condition-name has a value of FALSE when a GENERATE statement (see [GENERATE], page 286) causes a report group to be presented, the presentation of that group will be suppressed.
- 2. If the condition-name has a value of TRUE, the group will be presented.
- 3. See [Condition Names], page 41, for more information.

#### 6.9.35. PROMPT

#### **PROMPT Clause Syntax**

PROMPT [ CHARACTER IS literal-1 | identifier-1 ]

This syntax is valid in the following sections: SCREEN

This clause defines the character that will be used as the fill-character for any input fields on the screen.

- 1. The reserved word IS is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. The default prompt character, should no CHARACTER specification be coded, or should the PROMPT clause be absent altogether, is an underscore ('_').
- 3. Prompt characters will be automatically transformed into spaces upon input.

#### **6.9.36. PROTECTED**

### 

This syntax is valid in the following sections: SCREEN

The PROTECTED extended clause will effect the specified field to be limited in size, regardless of the picture size.  1 

- 1. The SIZE phrase specifies the size (length) of the field. After the ACCEPT or DISPLAY is finished, the cursor is placed immediately after the field defined by this clause, unless this would place the cursor outside of the current terminal window. In this case, the cursor is wrapped around to the beginning of the next line (scrolling the window if necessary).
- 2. If the SIZE phrase is not used, then the field length defaults to the size of the item being accepted or displayed. If the CONVERT phrase is used, however, then the size of the field depends on the data type of the item and the verb being used.
  - A. If the DISPLAY verb is executing, then the size is the same as if the CONVERT phrase were not specified except for numeric items. For numeric items, the size is the number of digits in the item, plus one if it is not an integer, plus one if it is signed. The remaining cases cover the size when an ACCEPT statement is used.
  - B. If the item is numeric or numeric edited, then the size is the number of digits in the item, plus one if it is not an integer, plus one if it is signed.
  - C. If the item is alphanumeric edited, then the size is set to the number of 'A' or 'X' positions specified in its PICTURE clause.
  - D. For all other data types, the field size is set to the size of the item (same as if CONVERT were not specified).
- 3. Note that the OUTPUT phrase changes the way in which the default field size is computed. See that heading above for details. Also note that the OUTPUT phrase affects only the way items are displayed on the screen; the internal format of accepted data is not affected.
- 4. Note that you cannot supply the CONVERT phrase in the Screen Section. Thus the size of a Screen Section field is always the size of its screen entry unless the SIZE phrase is specified.

¹ OR DOES IT? author uncertain

#### **6.9.37. REDEFINES**

#### **REDEFINES Clause Syntax**

REDEFINES identifier-1

 $This \ syntax \ is \ valid \ in \ the \ following \ sections: \ \texttt{FILE}, \ \texttt{WORKING-STORAGE}, \ \texttt{LOCAL-STORAGE}, \ \texttt{LINKAGE}$ 

The REDEFINES clause causes the data item in who's definition the REDEFINES clause is specified (hereafter referred to as the redefines object) to occupy the same physical storage space as *identifier-1* (hereafter referred to as the redefines subject).

- 1. The following rules must all be followed in order to use REDEFINES:
  - A. The level number of both the subject and object data items must be the same.
  - B. The level numbers of both the subject and object data items cannot be 66, 78 or 88.
  - C. If N represents the level number of the object, then no other data items with level number N may be defined between the subject and object data items unless they too are REDEFINES of the subject.
  - D. If N represents the level number of the object, then no other data items with a level number numerically less than N may be defined between the subject and object data items.
  - E. The total allocated size of the subject data item must be the same as the total allocated size of the object data item.
  - F. No OCCURS (see [OCCURS], page 172) clause may be part of the definition of either the subject or object data items. Either or both, however, may be group items that contain data items with OCCURS clauses.
  - G. No VALUE (see [VALUE], page 207) clause may be defined on the object data item, and no data items subordinate to the object data item may have VALUE clauses, with the exception of level-88 condition names.

#### 6.9.38. RENAMES

## RENAMES clause Syntax RENAMES identifier-1 [ THRU|THROUGH identifier-2

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE

The RENAMES clause regroups previously defined items by specifying alternative, possibly overlapping, groupings of elementary data items.

- 1. The reserved words THRU and THROUGH are interchangeable.
- 2. You must use the level number 66 for data description entries that contain the RENAMES clause.
- 3. The *identifier-1* and *identifier-2* data items, along with all data items defined between those two data items in the program source, must all be contained within the same 01-level record description.
- 4. See [66-Level Data Items], page 136, for additional information on the RENAMES clause.

#### **6.9.39. REQUIRED**

	REQUIRED Attribute Syntax
REQUIRED	

This syntax is valid in the following sections: SCREEN

This clause forces the user to enter data into the field it is specified on (or into all subordinate input-capable fields if REQUIRED is specified on a group item).

- 1. The EMPTY-CHECK (see [EMPTY-CHECK], page 154) and REQUIRED clauses are interchangeable, and may not be used together in the same data item description.
- 2. In order to take effect, the user must first move the cursor into the field having this clause in its definition.
- 3. The ACCEPT data-item statement (see [ACCEPT data-item], page 234) will ignore the Enter key and any other cursor-moving keystrokes that would cause the cursor to move to another screen item *unless* data has been entered into the field. Function keys will still be allowed to terminate the ACCEPT.
- 4. In order to be functional, this attribute must be supported by the underlying "curses" package your GnuCOBOL implementation was built with. As of this time, the "PDCurses" package (used for native Windows or MinGW builds) does not support REQUIRED.

#### 6.9.40. REVERSE-VIDEO

,	REVERSE-VIDEO Attribute Syntax
REVERSE-VIDEO	

This syntax is valid in the following sections: SCREEN

The REVERSE-VIDEO attribute swaps the specified or implied FOREGROUND-COLOR (see [FOREGROUND-COLOR], page 158) and BACKGROUND-COLOR (see [BACKGROUND-COLOR], page 144) attributes for the field whose definition contains this clause (or all subordinate fields if used on a group item).

#### 6.9.41. SECURE

	SECURE Attribute Syntax
SECURE	

This syntax is valid in the following sections: SCREEN

This clause will cause all data entered into the field to appear on the screen as asterisks.

- 1. The NO-ECHO (see [NO-ECHO], page 171) and SECURE clauses are interchangeable, and may not be used together in the same data item description.
- 2. This clause may only be used on a field allowing data entry (a field containing either the USING (see [USING], page 206) or TO (see [TO], page 195) clause).

#### 6.9.42. SIGN IS

### SIGN-IS Clause Syntax

SIGN IS LEADING TRAILING SEPARATE CHARACTER

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE, REPORT, SCREEN

This clause, allowable only for USAGE DISPLAY numeric data items, specifies how an 'S' symbol will be interpreted in a data item's picture clause.

- 1. The reserved words CHARACTER and IS are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. Without the SEPARATE CHARACTER option, the sign of the data item's value will be encoded by transforming the last (see TRAILING) or first (see LEADING) digit as follows:

First/Last Digit	Value For Positive	Value for Negative
0	0	p
1	1	q
2	2	r
3	3	$\mathbf{S}$
4	4	$\mathbf{t}$
5	5	u
6	6	V
7	7	W
8	8	X
9	9	У

- 3. If the SEPARATE CHARACTER clause is used, then an actual '+' or '-' character will be inserted into the field's value as the first (LEADING) or last (TRAILING) character. Note that having this character embedded within the data item's storage does not prevent the data item from being used as a source field in arithmetic operations.
- 4. When SEPARATE CHARACTER is specified, the 'S' symbol in the data item's PICTURE must be counted when determining the data item's size.
- 5. Neither the presence of an encoded digit (see above) nor an actual '+' or '-' character embedded within the data item's storage prevents the data item from being used as a source field in arithmetic operations.

#### 6.9.43. SOURCE

## SOURCE Clause Syntax SOURCE IS literal-1 | identifier-1 [ ROUNDED ]

This syntax is valid in the following sections: REPORT

This clause logically attaches a report section data item to another data item defined elsewhere in the data division.

- 1. The reserved word IS is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. When the report group containing this clause is presented, the value of the specified numeric literal or identifier will be automatically moved to the report data item prior to presentation.
- 3. The specified identifier may be defined anywhere in the data division, but if it is defined in the report section it may only be PAGE-COUNTER, LINE-COUNTER or a SUM (see [SUM], page 450) counter.
- 4. The PICTURE (see [PICTURE], page 176) of the report data item must be such that it would be legal to MOVE (see [MOVE], page 305) the specified literal or identifier to a data item with that PICTURE.
- 5. The ROUNDED option comes into play should the number of digits to the right of an actual or assumed decimal point be different between the specified literal or identifier value (the "source value") and the PICTURE specified for the field in whose definition the SOURCE clause appears (the "target field"). Without ROUNDED, excess digits in the source value will simply be truncated to fit the target field. With ROUNDED, the source value will be arithmetically rounded to fit the target field. See [ROUNDED], page 224, for information on the NEAREST-AWAY-FROM-ZERO rounding rule, which is the one that will apply.

#### 6.9.44. SUM OF

# SUM-OF Clause Syntax SUM OF { identifier-7 }... [ { RESET ON FINAL|identifier-8 } ] ~~~ { literal-2 } { ~~~~~~ } { UPON identifier-9 }

This syntax is valid in the following sections: REPORT

The SUM clause establishes a summation counter whose value will be arithmetically calculated whenever the field is presented.

- 1. The reserved words OF and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The SUM clause may only appear in a CONTROL FOOTING report group.
- 3. If the data item in which the SUM clause appears has been assigned its own identifier name, and that name is not FILLER, then that data item is referred to as a sum counter.
- 4. All identifier-7 data items must be non-edited numeric in nature.
- 5. If any identifier-7 data item is defined in the report section, it must be a sum counter.
- 6. Any identifier-7 data items that are sum counters must either be defined in the same report group as the data item in which this SUM clause appears or they must be defined in a report data item that exists at a lower level in this report's control hierarchy. See [Control Hierarchy], page 540, for additional information.
- 7. The PICTURE of the report data item in who's description this SUM clause appears in must be such that it would be legal to MOVE (see [MOVE], page 305) the specified *identifier-7* or *literal-2* value to a data item with that PICTURE.
- 8. The following points apply to the UPON option:
  - A. The data item *identifier-9* must be the name of a detail group specified in the same report as the control footing group in which this SUM clause appears.
  - B. The presence of an UPON clause limits the SUM clause to adding the specified numeric literal or identifier value into the sum counter only when a GENERATE identifier-9 statement is executed.
  - C. If there is no UPON clause specified, the value of *identifier-7* or *literal-2* will be added into the sum counter whenever a GENERATE (see [GENERATE], page 286) of any detail report group in the report is executed.
  - D. If there is only a single detail group in the report's definition, the UPON clause is meaningless.
- 9. The following points apply to the RESET option:
  - A. If the RESET option is coded, FINAL or *identifier-8* (whichever is coded on the RESET) must be one of the report's control breaks specified on the CONTROLS clause.
  - B. If there is no RESET option coded, the sum counter will be reset back to zero after each time the control footing containing the SUM clause is presented. This is the typical behaviour that would be expected.
  - C. If, however, you want to reset the SUM counter only when the control footing for a control break higher in the control hierarchy is presented, specify that higher control break on the RESET option.

#### 6.9.45. SYNCRONIZED

#### SYNCRONIZED Syntax

SYNCRONIZED|SYNCHRONISED [ LEFT|RIGHT ]


The LEFT and RIGHT (SYNCRONIZED) clauses are syntactically recognized but are otherwise non-functional.

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE

This optional clause optimizes the storage of binary numeric items to store them in such a manner as to make it as fast as possible for the CPU to fetch them.

- 1. The reserved words SYNCRONIZED and SYNCHRONISED are interchangeable, and may be abbreviated as SYNC.
- 2. If the SYNCRONIZED clause is coded on anything but a numeric data item with a USAGE (see [USAGE], page 198) that specifies storage of data in a binary form, the SYNCRONIZED clause will be ignored.
- 3. Synchronization is performed (by the compiler) as follows:
  - A. If the binary item occupies one byte of storage, no synchronization is performed.
  - B. If the binary item occupies two bytes of storage, the binary item is allocated at the next half-word boundary.
  - C. If the binary item occupies four bytes of storage, the binary item is allocated at the next word boundary.
  - D. If the binary item occupies four bytes of storage, the binary item is allocated at the next word boundary.

The following illustrates the allocation of a group of data items both without and with the SYNCRONIZED option. The grey blocks represent the unused bytes that are allocated in the Group-Item-2 structure because of the SYNC clauses.



#### 6.9.46. TO

	TO Clause Syntax	
TO identifier-5		

This syntax is valid in the following sections: SCREEN

This clause logically attaches a screen section data item to another data item defined elsewhere in the data division.

- 1. The TO clause is used to define a data-entry field with no initial value; when a value is entered, it will be saved to the specified identifier.
- 2. The FROM (see [FROM], page 159), TO, USING (see [USING], page 206) and VALUE (see [VALUE], page 207) clauses are mutually-exclusive in any screen section data item's definition.

#### 6.9.47. TYPE

```
TYPE Clause Syntax
[ TYPE IS { RH|{REPORT HEADING}}
                                                    } ]
         { ~~ ~~~~~ ~~~~~~
                                                    }
         { PH|{PAGE HEADING}
                                                    }
              ~~~~ ~~~~~~
 }
 { CH|{CONTROL HEADING} FINAL|identifier-2
 }
 { ~~ ~~~~~ ~~~~~
 }
 { DE|DETAIL
 }
 { ~~ ~~~~~
 }
 { CF|{CONTROL FOOTING} FINAL|identifier-2
 { PF|{PAGE FOOTING}
 }
 ~~ ~~~~ ~~~~~
 }
 { RF|{REPORT FOOTING}
 }
```

This syntax is valid in the following sections: REPORT

This clause defines the type of report group that is being defined for a report.

- 1. This clause is required on any 01-level data item definitions (other than 01-level constants) in the report section. This clause is invalid on any other report section data item definitions.
- 2. There may be a maximum of one (1) report group per RD defined with a TYPE of REPORT HEADING, PAGE HEADING, PAGE FOOTING and REPORT FOOTING.
- 3. There must be either a CONTROL HEADING or a CONTROL FOOTING or both specified for each entry specified on the CONTROLS ARE clause of the RD.
- 4. The various report groups that constitute a report may be defined in any order.
- 5. See [RWCS Lexicon], page 537, for a description of the seven different types of report groups.

#### **6.9.48. UNDERLINE**

	UNDERLINE Attribute Syntax
UNDERLINE	

This syntax is valid in the following sections: SCREEN

The UNDERLINE clause will introduce a horizontal line at the bottom edge of a screen field.

- 1. The LEFTLINE (see [LEFTLINE], page 165), OVERLINE (see [OVERLINE], page 175) and UNDERLINE clauses may be used in any combination in a single field's description.
- 2. This clause is essentially non-functional when used within Windows command shell (cmd.exe) environments and running programs compiled using a GnuCOBOL implementation built using "PDCurses" (such as Windows/MinGW builds).
- 3. Whether or not this clause operates on Cygwin or UNIX/Linux/OSX systems will depend upon the video attribute capabilities of the terminal output drivers and "curses" software being used.

#### 6.9.49. USAGE

	USAGE Clause Syntax	
USAGE IS data-item-usage		

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE, REPORT

The USAGE clause defines the format that will be used to store the value of a data item.

- 1. The reserved word IS is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. The following table summarizes the various USAGE specifications available in GnuCOBOL.  ${\tt BINARY}$

~~~~~

Range of Values: Defined by the quantity of '9's and the presence or

absence of an 'S' in the PICTURE

Storage Format: Compatible Binary Integer

Negative Values Allowed?: If PICTURE contains 'S'

PICTURE Used?: Yes

BINARY-C-LONG [ SIGNED ]

3. Depending on the system hardware, the range is either 0 to 2<sup>3</sup>1 or 0 to 2<sup>6</sup>3.

BINARY-C-LONG UNSIGNED

4. Depending on the system hardware, the range is either 0 to 2^32 or 0 to 2^64. This USAGE should only be used for direct CALLs into C and otherwise should not be used (and it won't compile with any strict -std as it is a GnuCOBOL-only extension).

BINARY-CHAR [ SIGNED ]

Range of Values: -128 – 127

Storage Format: Native Binary Integer

Negative Values Allowed?: Yes

PICTURE Used?: No

BINARY-CHAR UNSIGNED

Range of Values: 0-255

Storage Format: Native Binary Integer

Negative Values Allowed?: No

PICTURE Used?: No

BINARY-DOUBLE [ SIGNED ]

~~~~~~~~~~~

Range of Values: -9,223,372,036,854,775,808

9,223,372,036,854,775,807

Storage Format: Native Binary Integer

Negative Values Allowed?: Yes

PICTURE Used?: No

BINARY-DOUBLE UNSIGNED

Range of Values: 0 - 18,446,744,073,709,551,615

Storage Format: Native Binary Integer

Negative Values Allowed?: No

PICTURE Used?: No

BINARY-INT

Same as BINARY-LONG SIGNED

BINARY-LONG [ SIGNED ]

~~~~~~~

Range of Values: -2,147,483,648 - 2,147,483,647

Storage Format: Native Binary Integer

Negative Values Allowed?: Yes

PICTURE Used?: No

BINARY-LONG UNSIGNED

~~~~~~~~~

Range of Values: 0 - 4,294,967,295

Storage Format: Native Binary Integer

Negative Values Allowed?: No

PICTURE Used?: No

BINARY-LONG-LONG

~~~~~~~~~~~~~~~

Same as  ${\tt BINARY-DOUBLE}$   ${\tt SIGNED}$ 

BINARY-SHORT [ SIGNED ]

~~~~~~~~~~

Range of Values: -32,768 - 32,767

Storage Format: Native Binary Integer

Negative Values Allowed?: Yes

PICTURE Used?: No

BINARY-SHORT UNSIGNED

Range of Values: 0 - 65,535

Storage Format: Native Binary Integer

Negative Values Allowed?: No

PICTURE Used?: No

COMPUTATIONAL

~ ~ ~ ~

Same as BINARY

COMP [UTATIONAL] -1

~~~~ ~~

Same as FLOAT-SHORT

COMP [UTATIONAL] -2

~~~~ ~~

Same as FLOAT-LONG

COMP[UTATIONAL]-3

~~~~ ~~

Same as PACKED-DECIMAL

COMP [UTATIONAL] -4

~~~~ ~~

Same as BINARY

COMP [UTATIONAL] -5

~~~~ ~~

Range of Values: Depends on number of '9's in the PICTURE and the

binary-size setting of the configuration file used

to compile the program

Storage Format: Native Binary Integer

Negative Values Allowed?: If PICTURE contains 'S'

PICTURE Used?: Yes

COMP [UTATIONAL] -6

~~~~ ~~

Range of Values: Defined by the quantity of '9's and the presence or

absence of an 'S' in the PICTURE

Storage Format: Unsigned Packed Decimal

Negative Values Allowed?: No

PICTURE Used?: Yes

COMP [UTATIONAL] -X

~~~~ ~~

Range of Values: If used with PIC X, allocates one byte of storage

per 'X'; range of values is 0 to max storable in that many bytes. If used with PIC 9, range of values

depends on number of '9's in PICTURE

Storage Format: Native unsigned (X) or signed (9) Binary

Negative Values Allowed?: If PICTURE 9 and contains 'S'

PICTURE Used?: Yes

DISPLAY

Range of Values: Depends on PICTURE — One character per X, A,

9, period, \$, Z, 0, \*, S (if SEPARATE CHARACTER specified), +, - or B symbol in PICTURE; Add 2 more bytes if the DB or CR editing symbol is used

Storage Format: Characters

Negative Values Allowed?: If PICTURE contains 'S'

PICTURE Used?: Yes

FLOAT-DECIMAL-16

\* 10<sup>384</sup>

Storage Format: Native IEEE 754 Decimal64 Floating-point

Negative Values Allowed?: Yes

PICTURE Used?: No

FLOAT-DECIMAL-34

Range of Values:  $-9.99999... * 10^{6143} - 9.99999... * 10^{6144}$ 

Storage Format: Native IEEE 754 Decimal 128 Floating-point

Negative Values Allowed?: Yes

PICTURE Used?: No

 ${\tt FLOAT-LONG}$ 

Range of Values: Approximately -1.797693134862316 \* 10<sup>308</sup> -

 $1.797693134862316*10^{308}$ 

Storage Format: Native IEEE 754 Binary64 Floating-point

Negative Values Allowed?: Yes

PICTURE Used?: No

FLOAT-SHORT

Range of Values: Approximately  $-3.4028235 * 10^{38} - 3.4028235 *$ 

 $10^{38}$ 

Storage Format: Native IEEE 754 Binary32

Negative Values Allowed?: Yes

PICTURE Used?: No

INDEX

Range of Values: 0 to maximum address possible (32 or 64 bits)

Storage Format: Native Binary Integer

Negative Values Allowed?: No PICTURE Used?: No NATIONAL USAGE NATIONAL, while syntactically recognized, is not supported by GnuCOBOL PACKED-DECIMAL Range of Values: Defined by the quantity of '9's and the presence or absence of an 'S' in the PICTURE Storage Format: Signed Packed Decimal Negative Values Allowed?: If PICTURE contains 'S' PICTURE Used?: Yes POINTER ~~~~~~ Range of Values: 0 to maximum address possible (32 or 64 bits) Storage Format: Native Binary Integer Negative Values Allowed?: No PICTURE Used?: No PROCEDURE-POINTER Same as PROGRAM-POINTER PROGRAM-POINTER ~~~~~~~~~~~~~~ Range of Values: 0 to maximum address possible (32 or 64 bits) Storage Format: Native Binary Integer Negative Values Allowed?: No PICTURE Used?: No SIGNED-INT Same as BINARY-LONG SIGNED

SIGNED-LONG

Same as BINARY-DOUBLE SIGNED

SIGNED-SHORT

Same as BINARY-SHORT SIGNED

UNSIGNED-INT

Same as BINARY-LONG UNSIGNED

UNSIGNED-LONG

~~~~~~~~~

Same as BINARY-DOUBLE UNSIGNED

UNSIGNED-SHORT

~~~~~~~~~~~

Same as BINARY-SHORT UNSIGNED

5. Binary data (integer or floating-point) can be stored in either a *Big-Endian* or *Little-Endian* form.

Big-endian data allocation calls for the bytes that comprise a binary item to be allocated such that the least-significant byte is the right-most byte. For example, a four-byte binary item having a value of decimal 20 would be big-endian allocated as 00000014 (shown in hexadecimal notation).

Little-endian data allocation calls for the bytes that comprise a binary item to be allocated such that the least-significant byte is the left-most byte. For example, a four-byte binary item having a value of decimal 20 would be little-endian allocated as 14000000 (shown in hexadecimal notation).

All CPUs are capable of *understanding* big-endian format, which makes it the *most compatible* form of binary storage across computer systems.

Some CPUs — such as the Intel/AMD i386/x64 architecture processors used in most Windows PCs — prefer to process binary data stored in a little-endian format. Since that format is more efficient on those systems, it is referred to as the *native* binary format.

On a system supporting only one format of binary storage (generally, that would be bigendian), the terms *most efficient* and *native* format are synonymous.

- 6. Data items that have the UNSIGNED attribute explicitly coded, or DISPLAY, PACKED-DECIMAL, COMP-5, COMP-X items that do not have an 'S' symbol in their picture clause cannot preserve negative values that may be stored into them. Storing a negative value into such a field will actually result in the sign being stripped, essentially saving the absolute value in the data item.
- 7. Packed-decimal (i.e. USAGE PACKED-DECIMAL, USAGE COMP-3 or USAGE COMP-6) data is stored as a series of bytes such that each byte contains two 4-bit fields, referred to as nibbles (since they comprise half a "byte", they're just "nibbles" don't groan, I don't just make this stuff up!). Each nibble represents a '9' in the PICTURE and each holds a single decimal digit encoded as its binary value (0 = 0000, 1 = 0001, ..., 9 = 1001).

The *last* byte of a PACKED-DECIMAL or COMP-3 data item will always have its left nibble corresponding to the last '9' in the PICTURE and its right nibble reserved as a sign indicator.

This sign indicator is always present regardless of whether or not the PICTURE included an 'S' symbol.

The *first* byte of the data item will contain an unused left nibble if the PICTURE had an even number of '9' symbols in it.

The sign indicator will have a value of a hexadecimal A through F. Traditional packed decimal encoding rules call for hexadecimal values of F, A, C or E ("FACE") in the sign nibble to indicate a positive value and B or D to represent a negative value (hexadecimal digits 0-9 are undefined). Testing with a Windows MinGW/GnuCOBOL implementation shows that — in fact — hex digit D represents a negative number and any other hexadecimal digit denotes a positive number. Therefore, a PIC S9(3) COMP-3 packed-decimal field with a value of -15 would be stored internally as a hexadecimal 015D in GnuCOBOL.

If you attempt to store a negative number into a packed decimal field that has no 'S' in its PICTURE, the absolute value of the negative number will actually be stored.

USAGE COMP-6 does not allow for negative values, therefore no sign nibble will be allocated. A USAGE COMP-6 data item containing an odd number of '9' symbols in its PICTURE will leave its leftmost nibble unused.

- 8. The USAGE specifications FLOAT-DECIMAL-16 and FLOAT-DECIMAL-34 will encode data using IEEE 754 Decimal64 and Decimal128 format, respectively. The former allows for up to 16 digits of exact precision while the latter offers 34. The phrase "exact precision" is used because the traditional binary renderings of decimal real numbers in a floating-point format (FLOAT-LONG and FLOAT-SHORT, for example) only yield an approximation of the actual value because many decimal fractions cannot be precisely rendered in binary. The Decimal64 and Decimal128 renderings, however, render decimal real numbers in encoded decimal form in much the same way that PACKED-DECIMAL renders a decimal integer in digit-by-digit decimal form. The exact manner in which this rendering is performed is complex (Wikipedia has an excellent article on the subject just search for Decimal64).
- 9. GnuCOBOL stores FLOAT-DECIMAL-16 and FLOAT-DECIMAL-34 data items using either Big-Endian or Little-Endian form, whichever is native to the system.
- 10. The USAGE specifications FLOAT-LONG and FLOAT-SHORT use the IEEE 754 Binary64 and Binary32 formats, respectively. These are binary encodings of real decimal numbers, and as such cannot represent every possible value between the minimum and maximum values in the range for those usages. Wikipedia has an excellent article on the Binary64 and Binary32 encoding schemes just search on Binary32 or Binary64.
  - GnuCOBOL stores FLOAT-LONG and FLOAT-SHORT data items using either Big-Endian or Little-Endian form, whichever is native to the system.
- 11. A USAGE clause specified at the group item level will apply that USAGE to all subordinate data items, except those that themselves have a USAGE clause.
- 12. The only USAGE that is allowed in the report section is USAGE DISPLAY.

### 6.9.50. USING

|                    | USING Clause Syntax |
|--------------------|---------------------|
| USING identifier-1 |                     |
|                    |                     |

This syntax is valid in the following sections: SCREEN

This clause logically attaches a screen section data item to another data item defined elsewhere in the data division.

- 1. When the screen item whose definition this clause is part of is displayed, the value currently in *identifier-1* will be automatically moved into the screen item first.
- 2. When the screen item whose definition this clause is part of (or its parent) is accepted, the current contents of the screen item will be saved back to *identifier-1* at the conclusion of the ACCEPT.
- 3. The FROM (see [FROM], page 159), TO (see [TO], page 195), USING and VALUE (see [VALUE], page 207) clauses are mutually-exclusive in any screen section data item's definition.

### 6.9.51. VALUE

#### VALUE (Other Data Items) Syntax

```
VALUE IS [ALL] literal-1
```

This syntax is valid in the following sections: FILE, WORKING-STORAGE, LOCAL-STORAGE, LINKAGE, REPORT, SCREEN

The VALUE clause is used to define condition names or to assign values (at compilation time) to data items.

- 1. The reserved words ARE and IS are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. This clause cannot be specified on the same data item as a FROM (see [FROM], page 159), TO (see [TO], page 195) or USING (see [USING], page 206) clause.
- 3. The following points apply to using the VALUE clause in the definition of a condition name:
  - A. The clauses VALUE IS and VALUES ARE are interchangeable.
  - B. The reserved words THRU and THROUGH are interchangeable.
  - C. See [88-Level Data Items], page 139, for a discussion of how this format of VALUE is used to create condition names.
  - D. See [Condition Names], page 41, for a discussion of how condition names are used.
- 4. The following points apply to using the VALUE clause in the definition of any other data item:
  - A. In this context, VALUE specifies an initial compilation-time value that will be assigned to the storage occupied by the data item in the program object code generated by the compiler.
  - B. The VALUE clause is ignored on EXTERNAL (see [EXTERNAL], page 156) data items or on any data items defines as subordinate to an EXTERNAL data item.
  - C. This format of the VALUE clause may not be used anywhere in the description of an 01 item (or any of its subordinate items) serving as an FD or SD record description.
  - D. If the optional ALL clause is used, it may only be used with an alphanumeric literal value; the value will be repeated as needed to completely fill the data item. Here are some examples with and without ALL (the symbol b denotes a space):

```
PIC X(5) VALUE 'A' *> Abbbb
PIC X(5) VALUE ALL 'A' *> AAAAA
PIC 9(3) VALUE 1 *> 001
PIC 9(3) VALUE ALL '1' *> 111
```

- E. When used in the definition of a screen data item:
  - a. A figurative constant may not be supplied as literal-1.
  - b. Any FROM (see [FROM], page 159), TO (see [TO], page 195) or USING (see [USING], page 206) clause in the same data item's definition will be ignored.
  - c. If there is no picture clause specified, the size of the screen data item will be the length of the *literal-1* value.
  - d. If there is no picture clause and the ALL option is specified, the ALL option will be ignored.
- F. Giving a table an initial, compile-time value is one of the trickier aspects of COBOL data definition. There are basically three standard techniques and a fourth that people familiar with other COBOL implementations but new to GnuCOBOL may find interesting. So, here are the three *standard* approaches:
  - a. Don't bother worrying about it at compile-time. Use the INITIALIZE (see [INITIALIZE], page 292) to initialize all data item occurrences in a table (at run-time) to their data-type-specific default values (numerics: 0, alphabetic and alphanumerics: spaces).
  - b. Initialize small tables at compile time by including a VALUE clause on the group item that serves as a parent to the table, as follows:

```
05 SHIRT-SIZES VALUE "S 14M 15L 16XL17".

10 SHIRT-SIZE-TBL OCCURS 4 TIMES.

15 SST-SIZE PIC X(2).

15 SST-NECK PIC 9(2).
```

c. Initialize tables of almost any size at compilation time by utilizing the REDEFINES (see [REDEFINES], page 185) clause:

```
SHIRT-SIZE-VALUES.
 10 PIC X(4)
 VALUE "S 14".
 10 PIC X(4)
 VALUE "M 15".
 10 PIC X(4)
 VALUE "L 16".
 10 PIC X(4)
 VALUE "XL17".
05
 SHIRT-SIZES
 REDEFINES SHIRT-SIZE-VALUES.
 10 SHIRT-SIZE-TBL
 OCCURS 4 TIMES.
 15 SST-SIZE
 PIC X(2).
 15 SST-NECK
 PIC 9(2).
```

Admittedly, this table is much more verbose than the one shown with a group VALUE. What is good about this initialization technique, however, is that you can have as many FILLER and VALUE items as you need for a larger table, and those values can be as long as necessary!

G. Many COBOL compilers do not allow the use of VALUE and OCCURS (see [OCCURS], page 172) on the same data item; additionally, they don't allow a VALUE clause on a data item subordinate to an OCCURS. GnuCOBOL, however, has neither of these restrictions!

Observe the following example, which illustrates a fourth manner in which tables may be initialized in GnuCOBOL:

In this example, all six 'A' items will be initialized to '?', all six 'B' items will be initialized to '%' and all six 'N' items will be initialized to 10. It's not clear exactly how many times this sort of initialization will be useful, but it's there if you need it.

5. The FROM (see [FROM], page 159), TO (see [TO], page 195), USING (see [USING], page 206) and VALUE clauses are mutually-exclusive in any screen section data item's definition.

End of Chapter 6 — DATA DIVISION

# 7. PROCEDURE DIVISION

```
PROCEDURE DIVISION [{ USING Subprogram-Argument ... }]

{ CHAINING Main-Program-Argument ...}

[RETURNING identifier-1] .

[DECLARATIVES.]

[Event-Handler-Routine...]

[END DECLARATIVES.]

General-Program-Logic

[Nested-Subprogram...]

[END PROGRAM|FUNCTION name-1]
```

The PROCEDURE DIVISION of any GnuCOBOL program marks the point where all executable code is written.

### 7.1. PROCEDURE DIVISION USING

#### PROCEDURE DIVISION Subprogram-Argument Syntax

The USING clause defines the arguments that will be passed to a GnuCOBOL program which is serving as a subprogram.

- 1. The reserved words BY and IS are optional and may be omitted. The presence or absence of these words have no effect upon the program.
- 2. The USING clause should only be used on the procedure division header of subprograms (subroutines or user-defined functions).
- 3. The calling program will pass zero or more data items, known as arguments, to this sub-program there must be exactly as many *identifier-1* data items specified on the USING clause as the maximum number of arguments the subprogram will ever be passed.
- 4. If a subprogram does not expect any arguments, it should not have a USING clause specified on its procedure division header.
- 5. The order in which arguments are defined on the USING clause must correspond to the order in which those arguments will be passed to the subprogram by the calling program.
- 6. The identifiers specified on the USING clause must be defined in the linkage section of the subprogram. No storage is actually allocated for those identifiers in the subprogram as the actual storage for them will exist in the calling program.
- 7. A GnuCOBOL subprogram expects that all arguments to it will be one of two things:
  - The memory address of the actual data item (allocated in the calling program) that is being passed to the subprogram.
  - A numeric, full-word, binary value (i.e. USAGE BINARY-LONG (see [USAGE], page 198)) which is the actual argument being passed to the subprogram.

In the case of the former, the USING clause on the procedure division header should describe the argument via the BY REFERENCE clause — in the latter case, a BY VALUE specification should be coded. This allows the code generated by the compiler to properly reference the subprogram arguments at run-time.

- 8. BY REFERENCE is the assumed default for the first USING argument should no BY clause be specified for it. Subsequent arguments will assume the BY specification of the argument prior to them should they lack a BY clause of their own.
- 9. Changes made by a subprogram to the value of an argument specified on the USING clause will "be visible" to the calling program only if BY REFERENCE was explicitly specified or implicitly assumed for the argument on the subprogram's procedure division header and the argument was passed to the subprogram BY REFERENCE by the calling program. See [Subprogram Arguments], page 609, for additional information on the mechanics of how arguments are passed to subprograms.

- 10. The optional SIZE clause allows you to specify the number of bytes a BY VALUE argument will occupy, with SIZE DEFAULT specifying 4 bytes (this is the default if no SIZE clause is used), SIZE AUTO specifying the size of the argument in the calling program and SIZE integer-1 specifying a specific byte count.
- 11. The optional UNSIGNED keyword, legal only if SIZE AUTO or SIZE integer-1 are coded, will add the unsigned attribute to the argument's specification in the C-language function header code generated for the subprogram. While not of any benefit when the calling program is a GnuCOBOL program, this can improve compatibility with a C-language calling program.
- 12. The OPTIONAL keyword, legal only on BY REFERENCE arguments, allows calling programs to code OMITTED for that corresponding argument when they call this subprogram. See [CALL], page 253. for additional information on this feature.

### 7.2. PROCEDURE DIVISION CHAINING

#### PROCEDURE DIVISION Main-Program-Argument Syntax

```
[BY REFERENCE] [OPTIONAL] identifier-1
```

The CHAINING term provides one mechanism a programmer may use to retrieve command-line arguments passed to a program at execution time.

- 1. PROCEDURE DIVISION CHAINING may only be coded in a main program (that is, the first program executed when a compiled GnuCOBOL compilation unit is executed). It cannot be used in any form of subprogram.
- 2. The CHAINING clause defines arguments that will be passed to a main program from the operating system. The argument identifiers specified on the CHAINING clause will be populated by character strings comprised of the parameters specified to the program on the command line that executed it, as follows:
  - A. When a GnuCOBOL program is executed from a command-line, the complete command line text will be broken into a series of *tokens*, where each token is identified as being a word separated from the others in the command text by at least one space. For example, if the command line was /usr/local/myprog THIS IS A TEST, there will be five tokens identified by the operating system '/usr/local/myprog', 'THIS', 'IS', 'A' and 'TEST'.
  - B. Multiple space-delimited tokens may be treated as a single token by enclosing them in quotes. For example, there are only three tokens generated from the command line C:\Pgms\myprog.exe 'THIS IS A' TEST 'C:\Pgms\myprog.exe', 'THIS IS A' and 'TEST'. When quote characters are used to create multi-word tokens, the quote characters themselves are stripped from the token's value.
  - C. Once tokens have been identified, the first one (the command) will be discarded; the rest will be stored into the CHAINING arguments when the program begins execution, with the 2nd token going to the 1<sup>st</sup> argument, the 3rd token going to the 2nd argument and so forth.
  - D. If there are more tokens than there are arguments, the excess tokens will be discarded.
  - E. If there are fewer tokens than there are arguments, the excess arguments will be initialized as if the INITIALIZE identifier-1 (see [INITIALIZE], page 292) statement were executed.
  - F. All identifiers specified on the CHAINING clause should be defined as PIC X, PIC A, group items (which are treated implicitly as PIC X) or as PIC 9 USAGE DISPLAY. The use of USAGE BINARY (or the like) data items as CHAINING arguments is not recommended as all command-line tokens will be retained in their original character form as they are moved into the argument data items.
  - G. If an argument identifier is smaller in storage size than the token value to be stored in it, the right-most excess characters of the token value will be truncated as the value is moved in. Any JUSTIFIED RIGHT clause on such an argument identifier will be ignored.
  - H. If an argument is larger in storage size than the token value to be stored in it, the token value will be moved into the argument identifier in a left-justified manner. unmodified-modified byte positions in the identifier will be space filled, unless the argument iden-

tifier is defined as PIC 9 USAGE DISPLAY, in which case unmodified bytes will be filled with '0' characters from the systems native character set.

This behaviour when the argument is defined as PIC 9 may be unacceptable, as an argument defined as PIC 9(3) but passed in a value of '1' from the command line will receive a value of '100', not '001'. Consider defining "numeric" command line arguments as PIC X and then using the NUMVAL intrinsic function (see [NUMVAL], page 427) function to determine the proper numeric value.

### 7.3. PROCEDURE DIVISION RETURNING

#### PROCEDURE DIVISION RETURNING Syntax

| RETURNING | identifier-1 |
|-----------|--------------|
| ~~~~~~~   |              |

The RETURNING clause on the PROCEDURE DIVISION header documents that the subpro-

gram in which the clause appears will be returning a numeric value back to the program that called it.

- 1. The RETURNING clause is optional within a subroutine, as not all subroutines return a value to their caller.
- 2. The RETURNING clause is mandatory within a user-defined function, as all such must return a numeric result.
- 3. The identifier-1 data item should be defined as a USAGE BINARY-LONG data item.
- 4. Main programs that wish to "pass back" a return code value to the operating system when they exit do not use RETURNING - they do so simply by MOVEing a value to the RETURN-CODE special register.
- 5. This is not the only mechanism that a subprogram may use to pass a value back to its caller. Other possibilities are:
  - A. The subprogram may modify any argument that is specified as BY REFERENCE on its PROCEDURE DIVISION header. Whether the calling program can actually "see" any modifications depends upon how the calling program passed the argument to the subprogram. See [CALL], page 253, for more information.
  - B. A data item with the GLOBAL (see [GLOBAL], page 161) attribute specified in its description in the calling program is automatically visible to and updatable by a subprogram nested with the calling program. See [Independent vs Contained vs Nested Subprograms, page 603, for more information on subprogram nesting.
  - C. A data item defined with the EXTERNAL (see [EXTERNAL], page 156) attribute in a subprogram and the calling program (same name in both programs) is automatically visible to and updatable by both programs, even if those programs are compiled separately from one another.

## 7.4. PROCEDURE DIVISION Sections and Paragraphs

The procedure division is the only one of the COBOL divisions that allows you to create your own sections and paragraphs. These are collectively referred to as *Procedures*, and the names you create for those sections and paragraphs are called *Procedure Names*.

Procedure names are optional in the procedure division and — when used — are named entirely according to the needs and whims of the programmer.

Procedure names may be up to thirty one (31) characters long and may consist of letters, numbers, dashes and underscores. A procedure name may neither begin nor end with a dash ('-') or underscore ('\_') character. This means that Main, 0100-Read-Transaction and 17 are all perfectly valid procedure names.

There are three circumstances under which the use of certain GnuCOBOL statements or options will require the specification of procedures. These situations are:

- 1. When DECLARATIVES (see [DECLARATIVES], page 218) are specified.
- 2. When the ENTRY statement (see [ENTRY], page 275) is being used.
- 3. When any procedure division statement that references procedures is used. These statements are:
  - ALTER procedure-name
  - GO TO procedure-name
  - MERGE ... OUTPUT PROCEDURE procedure-name
  - PERFORM procedure-name
  - SORT ... INPUT PROCEDURE procedure-name and/or SORT ... INPUT PROCEDURE procedure-name

### 7.5. DECLARATIVES

#### **DECLARATIVES Syntax**

section-name-1 SECTION.

```
USE { [GLOBAL] AFTER STANDARD { EXCEPTION } PROCEDURE ON { INPUT
 } }
~~~ {
                    { ~~~~~ }
                                                                  } }
                                                     { OUTPUT
                             { ERROR
   {
                                       }
                                                                  } }
                                                     { ~~~~~
   {
                                                                  } }
                                                     { I-0
                                                                  } }
                                            } { ~~~
} { EXTEND
} { ~~~~~
                                                                  } }
   { FOR DEBUGGING ON { procedure-name-1
                    { ALL PROCEDURES
   {
                                                                  } }
   {
                     { REFERENCES OF identifier-1 }
   {
                                                     { file-name-1 } }
   {
                                                                    }
   { [ GLOBAL ] BEFORE REPORTING identifier-2
                                                                    }
                                                                    }
   { AFTER EC|{EXCEPTION CONDITION}
                                                                    }
           ~~ ~~~~~~~ ~~~~~~
```

The AFTER EXCEPTION CONDITION and AFTER EC clauses are syntactically recognized but are otherwise non-functional.

The DECLARATIVES area of the procedure division allows the programmer to define a series of "trap" procedures (referred to as declarative procedures) capable of intercepting certain events that may occur at program execution time. The syntax diagram above shows the format of a single such procedure.

- 1. The reserved words AFTER, FOR, ON, PROCEDURE and STANDARD are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. EC and EXCEPTION CONDITION are interchangeable.
- 3. The declaratives area may contain any number of declarative procedures, but no two declarative procedures should be coded to trap the same event.
- 4. The following points apply to the USE BEFORE REPORTING clause:
  - A. identifier-2 must be a report group.
  - B. At run-time, the declaratives procedure will be executed prior to the processing of the specified report group's presentation; within the procedure you may take either of the following actions:
    - You may adjust the value(s) of any items referenced in SUM (see [SUM], page 450) or SOURCE (see [SOURCE], page 191) clauses in the report group.
    - You may execute the SUPPRESS (see [SUPPRESS], page 352) statement to squelch the presentation of the specified report group altogether. Note that you will be suppressing this one specific instance of that group's presentation and not all of them.
- 5. The following points apply to the USE FOR DEBUGGING clause:
  - A. This clause allows you to define a declarative procedure that will be invoked whenever...

- ...identifier-1 is referenced on any statement.
- ...procedure-name-1 is executed.
- ...any procedure is executed (ALL PROCEDURES).
- B. A USE FOR DEBUGGING declarative procedure will be ignored at *compilation* time unless WITH DEBUGGING MODE is specified in the SOURCE-COMPUTER (see [SOURCE-COMPUTER], page 81) paragraph. Neither the compiler's -fdebugging-line switch nor -debug switch will activate this feature.
- C. Any USE FOR DEBUGGING declarative procedures will be ignored at *execution* time unless the COB\_SET\_DEBUG run-time environment variable (see [Run Time Environment Variables], page 584) has been set to a value of 'Y', 'y' or '1'.
- D. The typical use of a USE FOR DEBUGGING declarative procedure is to display the DEBUG-ITEM special register, which will be implicitly and automatically created in your program for you if WITH DEBUGGING MODE is active.

The structure of DEBUG-ITEM will be as follows:

```
O1 DEBUG-ITEM.
```

| 05 DEBUG-LINE     | PIC X(6).                        |
|-------------------|----------------------------------|
| 05 FILLER         | PIC X(1) VALUE SPACE.            |
| 05 DEBUG-NAME     | PIC X(31).                       |
| 05 FILLER         | PIC X(1) VALUE SPACE.            |
| 05 DEBUG-SUB-1    | PIC S9(4) SIGN LEADING SEPARATE. |
| 05 FILLER         | PIC X(1) VALUE SPACE.            |
| 05 DEBUG-SUB-2    | PIC S9(4) SIGN LEADING SEPARATE. |
| 05 FILLER         | PIC X(1) VALUE SPACE.            |
| 05 DEBUG-SUB-3    | PIC S9(4) SIGN LEADING SEPARATE. |
| 05 FILLER         | PIC X(1) VALUE SPACE.            |
| 05 DEBUG-CONTENTS | PIC X(31).                       |

### where...

#### DEBUG-LINE

... is the program line number of the statement that triggered the declaratives procedure.

#### DEBUG-NAME

. . . is the procedure name or identifier name that triggered the declaratives procedure.

#### DEBUG-SUB-1

... is the first subscript value (if any) for the reference of the identifier that triggered the declaratives procedure.

#### DEBUG-SUB-2

... is the second subscript value (if any) for the reference of the identifier that triggered the declaratives procedure.

### DEBUG-SUB-3

... is the third subscript value (if any) for the reference of the identifier that triggered the declaratives procedure.

#### DEBUG-CONTENTS

... is a (brief) statement of the manner in which the procedure that triggered the declaratives procedure was executed or the first 31 characters of the value of the identifier whose reference triggered the declaratives procedure (the value after the statement was executed).

- 6. The USE AFTER STANDARD ERROR PROCEDURE clause defines a declarative procedure invoked any time a failure is encountered with the specified I/O type (or against the specified file(s)).
- 7. The GLOBAL (see [GLOBAL], page 161) option, if used, allows a declarative procedure to be used across the program containing the USE statement and any subprograms nested within that program.
- 8. Declarative procedures may not reference any other procedures defined outside the scope of DECLARATIVES.

### 7.6. Common Clauses on Executable Statements

### 7.6.1. AT END + NOT AT END

```
AT END Syntax

[ AT END imperative-statement-1 ]

[ NOT AT END imperative-statement-2 ]

----
```

AT END clauses may be specified on READ (see [READ], page 316), RETURN (see [RETURN], page 323), SEARCH (see [SEARCH], page 327) and SEARCH ALL (see [SEARCH ALL], page 328) statements.

- 1. The following points pertain to the use of these clauses on READ (see [READ], page 316) and RETURN (see [RETURN], page 323) statements:
  - A. The AT END clause will if present cause imperative-statement-1 (see [Imperative Statement], page 632) to be executed if the statement fails due to a file status of 10 (end-of-file). See [File Status Codes], page 98, for a list of possible File Status codes.
    - An AT END clause will not detect other non-zero file-status values.
    - Use a DECLARATIVES (see [DECLARATIVES], page 218) routine or an explicitly-declared file status field tested after the READ or RETURN to detect error conditions other than end-of-file.
  - B. A NOT AT END clause will cause *imperative-statement-2* to be executed if the READ or RETURN attempt is successful.
- 2. The following points pertain to the use of these clauses on SEARCH (see [SEARCH], page 327) and SEARCH ALL (see [SEARCH ALL], page 328) statements:
  - A. An AT END clause detects and handles the case where either form of table search has failed to locate an entry that satisfies the search conditions being used.
  - B. The NOT AT END clause is not allowed on either form of table search.

### 7.6.2. CORRESPONDING

Three GnuCOBOL statements — ADD (see [ADD CORRESPONDING], page 249), MOVE (see [MOVE CORRESPONDING], page 306) and SUBTRACT (see [SUBTRACT CORRESPONDING], page 351) support the use of a CORRESPONDING option:

```
ADD CORRESPONDING group-item-1 TO group-item-2
MOVE CORRESPONDING group-item-1 TO group-item-2
SUBTRACT CORRESPONDING group-item-1 FROM group-item-2
```

This option allows one or more data items within one group item (group-item-1 — the first named on the statement) to be paired with correspondingly-named (hence the name) in a second group item (group-item-2 — the second named on the statement). The contents of group-item-1 will remain unaffected by the statement while one or more data items within group-item-2 will be changed.

In order for data-item-1, defined subordinate to group item group-item-1 to be a corresponding match to data-item-2 which is subordinate to group-item-2, each of the following must be true:

- 1. Both data-item-1 and data-item-2 must have the same name, and that name may not explicitly or implicitly be FILLER.
- 2. Both data-item-1 and data-item-2...
  - A. ... must exist at the same relative structural "depth" of definition within group-item-1 and group-item-2, respectively
  - B. ...and all "parent" data items defined within each group item must have identical (but non-FILLER) names.
- 3. When used with a MOVE verb...
  - A. ... one of data-item-1 or data-item-2 (but not both) is allowed to be a group item
  - B. ...and it must be valid to move data-item-1 TO data-item-2.
- 4. When used with ADD or SUBTRACT verbs, both data-item-1 and data-item-2 must be numeric, elementary, unedited items.
- 5. Neither data-item-1 nor data-item-2 may be a REDEFINES (see [REDEFINES], page 185) or RENAMES (see [RENAMES], page 186) of another data item.
- 6. Neither data-item-1 nor data-item-2 may have an OCCURS (see [OCCURS], page 172) clause, although either may contain subordinate data items that do have an OCCURS clause (assuming rule 3a applies)

Observe the definitions of data items 'Q' and 'Y'...

| 01 | Q. |    |     |        |      |           | 01 | Υ. |     |      |      |            |
|----|----|----|-----|--------|------|-----------|----|----|-----|------|------|------------|
|    | 03 | Х. |     |        |      |           |    | 02 | Α   |      | PIC  | X(1).      |
|    |    | 05 | Α   |        | PIC  | 9(1).     |    | 02 | G1. | •    |      |            |
|    |    | 05 | G1. |        |      |           |    |    | 03  | G2.  |      |            |
|    |    |    | 10  | G2.    |      |           |    |    |     | 04 B | PIC  | X(1).      |
|    |    |    |     | 15 B   | PIC  | X(1).     |    | 02 | С   |      | PIC  | X(1).      |
|    |    | 05 | C.  |        |      |           |    | 02 | G3  | •    |      |            |
|    |    |    | 10  | FILLER | PIC  | X(1).     |    |    | 03  | G5.  |      |            |
|    |    | 05 | G3. | •      |      |           |    |    |     | 04 D | PIC  | X(1).      |
|    |    |    | 10  | G4.    |      |           |    |    | 03  | G6   | PIC  | X(1).      |
|    |    |    |     | 15 D   | PIC  | X(1).     |    | 02 | E   |      | PIC  | 9(1).      |
|    |    | 05 | E   |        | PIC  | X(1).     |    | 02 | F   |      | PIC  | X(1).      |
|    |    | 05 | F   |        | REDE | EFINES V1 |    | 02 | G   |      | PIC  | X(4).      |
|    |    |    |     |        | PIC  | X(1).     |    | 02 | Η   |      | OCCU | RS 4 TIMES |

```
05 G.
                                             PIC X(1).
   10 G6
             OCCURS 4 TIMES 66 I
                                             RENAMES E.
             PIC X(1).
                               02 J.
05 H
             PIC X(4).
                                  03 K.
05 I
             PIC 9(1).
                                     04 L.
                                        05 M.
05 J.
   10 K.
      15 M
             PIC X(1).
```

The following are the valid CORRESPONDING matches, assuming the statement MOVE CORRESPONDING X TO Y is being executed (there are no valid corresponding matches for ADD CORRESPONDING or SUBTRACT CORRESPONDING because every potential match up violates rule #4):

The following are the CORRESPONDING match ups that passed rule #1 (but failed on another rule), and the reasons why they failed.

| Data | Failure Reason           |
|------|--------------------------|
| Item |                          |
| D    | Fails due to rule $\#2b$ |
| E    | Fails due to rule $\#3b$ |
| F    | Fails due to rule $\#5$  |
| G1   | Fails due to rule #3a    |
| G2   | Fails due to rule #3a    |
| G3   | Fails due to rule #3a    |
| G4   | Fails due to rule #1     |
| G5   | Fails due to rule #1     |
| G6   | Fails due to rule #6     |
| H    | Fails due to rule #6     |
| I    | Fails due to rule #5     |
| J    | Fails due to rule #3a    |
| K    | Fails due to rule #3a    |
| L    | Fails due to rule #1     |
| M    | Fails due to rule #2a    |

### 7.6.3. INVALID KEY + NOT INVALID KEY

# INVALID KEY Syntax

```
[ INVALID KEY imperative-statement-1 ]

"""

[ NOT INVALID KEY imperative-statement-2 ]
```

INVALID KEY clauses may be specified on DELETE (see [DELETE], page 262), READ (see [Random READ], page 318), REWRITE (see [REWRITE], page 324), START (see [START], page 343) and WRITE (see [WRITE], page 360) statements.

Specification of an INVALID KEY clause will allow your program to trap an I/O failure condition (with an I/O error code in the file's FILE-STATUS (see [SELECT], page 95) field) that has

occurred due to a record-not-found condition and handle it gracefully by executing *imperative-statement-1* (see [Imperative Statement], page 632).

An optional NOT INVALID KEY clause will cause *imperative-statement-2* to be executed if the statement's execution was successful.

#### 7.6.4. ON EXCEPTION + NOT ON EXCEPTION

```
ON EXCEPTION Syntax

[ ON EXCEPTION imperative-statement-1 ]

[ NOT ON EXCEPTION imperative-statement-2 ]
```

EXCEPTION clauses may be specified on ACCEPT (see [ACCEPT], page 230), CALL (see [CALL], page 253) and DISPLAY (see [DISPLAY], page 263) statements.

Specification of an exception clause will allow your program to trap a failure condition that has occurred and handle it gracefully by executing *imperative-statement-1* (see [Imperative Statement], page 632). If such a condition occurs at runtime without having one of these clauses specified, an error message will be generated (by the GnuCOBOL runtime library) to the SYSERR device (pipe 2). The program may also be terminated, depending upon the type and severity of the error.

An optional NOT ON EXCEPTION clause will cause *imperative-statement-2* to be executed if the statement's execution was successful.

#### 7.6.5. ON OVERFLOW + NOT ON OVERFLOW

OVERFLOW clauses may be specified on CALL (see [CALL], page 253), STRING (see [STRING], page 347) and UNSTRING (see [UNSTRING], page 356) statements.

An ON OVERFLOW clause will allow your program to trap a failure condition that has occurred and handle it gracefully by executing *imperative-statement-1* (see [Imperative Statement], page 632). If such a condition occurs at runtime without having one of these clauses specified, an error message will be generated (by the GnuCOBOL runtime library) to the SYSERR device (pipe 2). The program may also be terminated, depending upon the type and severity of the error

An optional NOT ON OVERFLOW clause will cause *imperative-statement-2* to be executed if the statement's execution was successful.

### 7.6.6. ON SIZE ERROR + NOT ON SIZE ERROR

#### ON SIZE ERROR Syntax

SIZE ERROR clauses may be included on ADD (see [ADD], page 245), COMPUTE (see [COMPUTE], page 260), DIVIDE (see [DIVIDE], page 269), MULTIPLY (see [MULTIPLY], page 307) and SUBTRACT (see [SUBTRACT], page 349) statements.

Including an ON SIZE ERROR clause on an arithmetic statement will allow your program to trap a failure of an arithmetic statement (either generating a result too large for the receiving field, or attempting to divide by zero) and handle it gracefully by executing *imperative-statement-1* (see [Imperative Statement], page 632). Field size overflow conditions occur silently, usually without any runtime messages being generated, even though such events rarely lend themselves to generating correct results. Division by zero errors, when no ON SIZE ERROR clause exists, will produce an error message (by the GnuCOBOL runtime library) to the SYSERR device (pipe 2) and will also abort the program.

An optional NOT ON SIZE ERROR clause will cause imperative-statement-2 to be executed if the arithmetic statement's execution was successful.

### **7.6.7. ROUNDED**



GnuCOBOL provides for control over the final rounding process applied to the receiving fields on all arithmetic verbs. Each of the arithmetic statements (ADD (see [ADD], page 245), COMPUTE (see [COMPUTE], page 260), DIVIDE (see [DIVIDE], page 269), MULTIPLY (see [MULTIPLY], page 307) and SUBTRACT (see [SUBTRACT], page 349)) statements allow an optional ROUNDED clause to be applied to each receiving data item.

The following rules apply to the rounding behaviour induced by this clause.

- 1. Rounding only applies when the result being saved to a receiving field with a ROUNDED clause is a non-integer value.
- 2. Absence of a ROUNDED clause is the same as specifying ROUNDED MODE IS TRUNCATION.
- 3. Use of a ROUNDED clause without a MODE specification is the same as specifying ROUNDED MODE IS NEAREST-AWAY-FROM-ZERO.

The behaviour of the eight different rounding modes is defined in the following table. Note that a '...' indicates the last digit repeats. The examples assume an integer receiving field.

#### AWAY-FROM-ZERO

Rounding is to the nearest value of larger magnitude.

| $+3.510 \Rightarrow +4$ |
|-------------------------|
| $+3.500 \Rightarrow +4$ |
| $+3.499 \Rightarrow +4$ |
| $+2.500 \Rightarrow +3$ |
| $+2.499 \Rightarrow +3$ |
|                         |

#### NEAREST-AWAY-FROM-ZERO

Rounding is to the nearest value (larger or smaller). If two values are equally near, the value with the larger absolute value is selected.

| $-3.510 \Rightarrow -4$ | $+3.510 \Rightarrow +4$ |
|-------------------------|-------------------------|
| $-3.500 \Rightarrow -4$ | $+3.500 \Rightarrow +4$ |
| $-3.499 \Rightarrow -3$ | $+3.499 \Rightarrow +3$ |
| $-2.500 \Rightarrow -3$ | $+2.500 \Rightarrow +3$ |
| $-2.499 \Rightarrow -2$ | $+2.499 \Rightarrow +2$ |

#### NEAREST-EVEN

Rounding is to the nearest value (larger or smaller). If two values are equally near, the value whose rightmost digit is *even* is selected. This mode is sometimes called "Banker's rounding".

| $-3.510 \Rightarrow -4$ | $+3.510 \Rightarrow +4$ |
|-------------------------|-------------------------|
| $-3.500 \Rightarrow -4$ | $+3.500 \Rightarrow +4$ |
| $-3.499 \Rightarrow -3$ | $+3.499 \Rightarrow +3$ |
| $-2.500 \Rightarrow -2$ | $+2.500 \Rightarrow +2$ |
| $-2.499 \Rightarrow -2$ | $+2.499 \Rightarrow +2$ |

### NEAREST-TOWARD-ZERO

Rounding is to the nearest value (larger or smaller). If two values are equally near, the value with the smaller absolute value is selected.

| $-3.510 \Rightarrow -4$ | $+3.510 \Rightarrow +4$ |
|-------------------------|-------------------------|
| $-3.500 \Rightarrow -3$ | $+3.500 \Rightarrow +3$ |
| $-3.499 \Rightarrow -3$ | $+3.499 \Rightarrow +3$ |
| $-2.500 \Rightarrow -2$ | $+2.500 \Rightarrow +2$ |
| $-2.499 \Rightarrow -2$ | $+2.499 \Rightarrow +2$ |

#### PROHIBITED

No rounding is performed. If the value cannot be represented exactly in the desired format, the EC-SIZE-TRUNCATION condition (exception code 1005) is set (and may be retrieved via the ACCEPT (see [ACCEPT FROM Runtime-Info], page 242) statement) and the results of the operation are undefined.

| $-3.510 \Rightarrow \text{Undefined}$ | $+3.510 \Rightarrow \text{Undefined}$ |
|---------------------------------------|---------------------------------------|
| $-3.500 \Rightarrow \text{Undefined}$ | $+3.500 \Rightarrow \text{Undefined}$ |
| $-3.499 \Rightarrow Undefined$        | $+3.499 \Rightarrow Undefined$        |

| $-2.500 \Rightarrow \text{Undefined}$ | $+2.500 \Rightarrow \text{Undefined}$ |
|---------------------------------------|---------------------------------------|
| $-2.499 \Rightarrow \text{Undefined}$ | $+2.499 \Rightarrow Undefined$        |

### TOWARD-GREATER

Rounding is toward the nearest value whose algebraic value is larger.

| $-3.510 \Rightarrow -3$ | $+3.510 \Rightarrow +4$ |
|-------------------------|-------------------------|
| $-3.500 \Rightarrow -3$ | $+3.500 \Rightarrow +4$ |
| $-3.499 \Rightarrow -3$ | $+3.499 \Rightarrow +4$ |
| $-2.500 \Rightarrow -2$ | $+2.500 \Rightarrow +3$ |
| $-2.499 \Rightarrow -2$ | $+2.499 \Rightarrow +3$ |

### TOWARD-LESSER

Rounding is toward the nearest value whose algebraic value is smaller.

| $-3.510 \Rightarrow -4$ | $+3.510 \Rightarrow +3$ |
|-------------------------|-------------------------|
| $-3.500 \Rightarrow -4$ | $+3.500 \Rightarrow +3$ |
| $-3.499 \Rightarrow -4$ | $+3.499 \Rightarrow +3$ |
| $-2.500 \Rightarrow -3$ | $+2.500 \Rightarrow +2$ |
| $-2.499 \Rightarrow -3$ | $+2.499 \Rightarrow +2$ |

### TRUNCATION

Rounding is to the nearest value whose magnitude is smaller.

| $-3.510 \Rightarrow -3$ | $+3.510 \Rightarrow +3$ |
|-------------------------|-------------------------|
| $-3.500 \Rightarrow -3$ | $+3.500 \Rightarrow +3$ |
| $-3.499 \Rightarrow -3$ | $+3.499 \Rightarrow +3$ |
| $-2.500 \Rightarrow -2$ | $+2.500 \Rightarrow +2$ |
| $-2.499 \Rightarrow -2$ | $+2.499 \Rightarrow +2$ |

## 7.7. Special Registers

GnuCOBOL, like other COBOL dialects, includes a number of data items that are automatically available to a programmer without the need to actually define them in the data division. COBOL refers to such items as registers or special registers. The special registers available to a GnuCOBOL program are as follows:

### COB-CRT-STATUS

PIC 9(4) — This is the default data item allocated for use by the ACCEPT data-item statement (see [ACCEPT data-item], page 234), if no CRT STATUS (see [SPECIAL-NAMES], page 84) clause was specified..

#### DEBUG-TTEM

Group Item — A group item in which debugging information generated by a USE FOR DEBUGGING section in the declaratives area of the procedure division will place information documenting why the USE FOR DEBUGGING procedure was invoked. Consult the DECLARATIVES (see [DECLARATIVES], page 218) documentation for information on the structure of this register.

#### LINAGE-COUNTER

BINARY-LONG SIGNED — An occurrence of this register exists for each selected file having a LINAGE (see [File/Sort-Description], page 113) clause. If there are multiple files whose file descriptions have LINAGE clauses, any explicit references to this register will require qualification (using OF file-name). The value of this register will be the current logical line number within the page body. The value of this register cannot be modified.

#### LINE-COUNTER

BINARY-LONG SIGNED — An occurrence of this register exists for each report defined in the program (via an RD (see [REPORT SECTION], page 124)). If there are multiple reports, any explicit references to this register not made in the report section will require qualification (OF report-name). The value of this register will be the current logical line number on the current page. The value of this register cannot be modified.

#### NUMBER-OF-CALL-PARAMETERS

BINARY-LONG SIGNED — This register contains the number of arguments passed to a subroutine — the same value that would be returned by the C\$NARG built-in system subroutine (see [C\$NARG], page 485). Its value will be zero when referenced in a main program. This register, when referenced from within a user-defined function, returns a value of one ('1') if the function has any number of arguments and a zero if it has no arguments.

#### PAGE-COUNTER

BINARY-LONG SIGNED — An occurrence of this register exists for each report having an RD (see [REPORT SECTION], page 124). If there are multiple such reports, any explicit references to this register not made in the report section will require qualification (OF report-name). The value of this register will be the current report page number. The value of this register cannot be modified.

#### RETURN-CODE

BINARY-LONG SIGNED — This register provides a numeric data item into which a subroutine may MOVE (see [MOVE], page 305) a value (which will then be available to the calling program) prior to transferring control back to the program that called it, or into which a main program may MOVE a value before returning control to the

operating system. Many built-in subroutines will return a value using this register. These values are — by convention — used to signify success (usually with a value of 0) or failure (usually with a non-zero value) of the process the program was attempting to perform. This register may also be modified by a subprogram as a result of that subprogram's use of the RETURNING (see [PROCEDURE DIVISION RETURNING], page 216) clause.

#### SORT-RETURN

BINARY-LONG SIGNED — This register is used to report the success/fail status of a RELEASE (see [RELEASE], page 321) or RETURN (see [RETURN], page 323) statement. A value of 0 is reported on success. A value of 16 denotes failure. An AT END (see [AT END + NOT AT END], page 220) condition on a RETURN is not considered a failure.

#### WHEN-COMPILED

PIC X(16) — This register contains the date and time the program was compiled in the format 'mm/dd/yyhh.mm.ss'. Note that only a two-digit year is provided.

#### LENGTH OF Syntax

LENGTH OF numeric-literal-1 | identifier-1

Alphanumeric literals and identifiers may optionally be prefixed with the LENGTH OF clause. The compile-time value generated by this clause will be the number of bytes in the alphanumeric literal or the defined size (in bytes) of the identifier.

1. The reserved word OF is optional and may be omitted. The presence or absence of this word has no effect upon the program. Here is an example. The following two GnuCOBOL statements both display the same result (27):

```
O1 Demo-Identifier PIC X(27).
...
DISPLAY LENGTH OF "This is a LENGTH OF Example"
DISPLAY LENGTH OF Demo-Identifier
```

- 2. The LENGTH OF clause on a literal or identifier reference may generally be used anywhere a numeric literal might be specified, with the following exceptions:
  - As part of the FROM clause of a WRITE (see [WRITE], page 360) or RELEASE statement (see [RELEASE], page 321).
  - As part of the TIMES clause of a PERFORM statement (see [PERFORM], page 311).

### 7.8. GnuCOBOL Statements

### 7.8.1. ACCEPT

### 7.8.1.1. ACCEPT FROM CONSOLE

This format of the ACCEPT statement is used to read a value from the console window or the standard input device and store it into a data item (identifier-1).

- 1. If no FROM clause is specified, FROM CONSOLE is assumed.
- 2. The specified *mnemonic-name-1* must either be one of the built-in device names CONSOLE, STDIN, SYSIN or SYSIPT, or a user-defined (see [SPECIAL-NAMES], page 84) mnemonic name *attached* to one of those four device names.
- 3. Input will be read either from the console window (CONSOLE) or from the system-standard input (pipe 0 = STDIN, SYSIN or SYSIPT) and will be saved in *identifier-1*.
- 4. If identifier-1 is a numeric data item, the character value read from the console or standard-input device will be parsed according to the rules for input to the NUMVAL intrinsic function (see [NUMVAL], page 427), except that none of the trailing sign formats are honoured.

### 7.8.1.2. ACCEPT FROM COMMAND-LINE

# ACCEPT FROM COMMAND-LINE Syntax

```
ACCEPT identifier-1

FROM { COMMAND-LINE }

{ ARGUMENT-NUMBER }

{ ARGUMENT-VALUE }

{ ARGUMENT-VALUE }

{ COMMAND-LINE }

{ NOT ON EXCEPTION imperative-statement-1 }

{ END-ACCEPT }

END-ACCEPT ]
```

This format of the ACCEPT statement is used to retrieve information from the program's command line.

- 1. The reserved word ON is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. When you accept from the COMMAND-LINE option, you will retrieve the entire set of arguments entered on the command line that executed the program, exactly as they were specified. Parsing that returned data into its meaningful information will be your responsibility.
- 3. Using COMMAND-LINE or ARGUMENT-VALUE in a \*nix based platform and that includes Linux, OSX, BSD and under windows running msys or MinGW etc, the shell process will expand any arguments that have a '\*' in the list such as 'a\*', 'abc\*.\*', etc. and create a list of all files that match the pattern. To avoid this if not wanted, put all such argument within quotes, e.g., progundertest "a\*" b c d "ef\*" "\*hg" and the text within quotes will be passed verbatim to the program (as in the example progundertest).
- 4. By accepting from ARGUMENT-NUMBER, you will be asking the GnuCOBOL run-time system to parse the arguments from the command line and return the number of arguments found. Parsing will be conducted according to the following rules:
  - A. Arguments will be separated by treating spaces and/or tab characters as the delimiters between arguments. The number of such delimiters separating two non-blank argument values is irrelevant.
  - B. Strings enclosed in double-quote characters ('"') will be treated as a single argument, regardless of how many spaces or tab characters (if any) might be embedded within the quotation characters.
  - C. On Windows systems, single-quote, or apostrophe, characters ('') will be treated just like any other data character and will *not* delineate argument strings.
- 5. By accepting from ARGUMENT-VALUE, you will be asking the GnuCOBOL run-time system to parse the arguments from the command line and return the "current" argument. You specify which argument number is "current" via the ARGUMENT-NUMBER option on the DISPLAY statement (see [DISPLAY UPON COMMAND-LINE], page 264). Parsing of arguments will be conducted according to the rules set forth above.

6. The optional ON EXCEPTION and NOT ON EXCEPTION clauses may be used to detect and react to the failure or success, respectively, of an attempt to retrieve an ARGUMENT-VALUE. See [ON EXCEPTION + NOT ON EXCEPTION], page 223, for additional information.

### 7.8.1.3. ACCEPT FROM ENVIRONMENT

#### ACCEPT FROM ENVIRONMENT Syntax

```
ACCEPT identifier-1
                                           }
        FROM { ENVIRONMENT-VALUE
        ~~~ { ~~~~~~~~~~~
 }
 { ENVIRONMENT { literal-1
 { ~~~~~~ { identifier-1 } }
 [ON EXCEPTION imperative-statement-1]
 [NOT ON EXCEPTION imperative-statement-2]
[END-ACCEPT]
```

This format of the ACCEPT statement is used to retrieve environment variable values.

- 1. The reserved word ON is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. By accepting from ENVIRONMENT-VALUE, you will be asking the GnuCOBOL run-time system to retrieve the value of the environment variable whose name is currently in the ENVIRONMENT-NAME register. A value may be placed into the ENVIRONMENT-NAME register using the ENVIRONMENT-NAME option of the DISPLAY statement (see [DISPLAY UPON ENVIRONMENT-NAME], page 265).
- 3. A simpler approach to retrieving an environment variables value is to use the ENVIRONMENT option, where you specify the environment variable whose value is to be retrieved right on the ACCEPT statement itself.
- 4. The optional ON EXCEPTION and NOT ON EXCEPTION clauses may be used to detect and react to an attempt to retrieve the value of a non-existent environment variable or the successful retrieval of an environment variable's value, respectively. See [ON EXCEPTION + NOT ON EXCEPTION, page 223, for additional information.

### 7.8.1.4. ACCEPT data-item

# ACCEPT data-item Syntax ACCEPT { identifier-1 } { OMITTED ~~~~~~ [{ FROM EXCEPTION-STATUS }] ~~~~ ~~~~~~~~~~~~ [{ FROM CRT ] [ MODE IS BLOCK ]} ~~~~ [ AT { | LINE NUMBER { integer-1 | } ] ~~ { | ~~~~ { identifier-2 } | } { | COLUMN|COL|POSITION|POS NUMBER { integer-2 { identifier-3 } { } { { integer-3 } } { { identifier-4 } } [ WITH [ Attribute-Specification ]... [ LOWER | UPPER ] ~~~~ ~~~~ [ SCROLL { UP } [ { integer-4 } LINE|LINES ] ] ~~~~~ { ~~ } { identifier-5 } { DOWN } [ TIMEOUT|TIME-OUT AFTER { integer-5 } ] ~~~~~~ { identifier-6 } [ CONVERSION ] ~~~~~~~~ [ UPDATE ] ~~~~~ [SIZE { integer-6 } ] ~~~~ { identifier-7 } [ ON EXCEPTION imperative-statement-1 ] [ NOT ON EXCEPTION imperative-statement-2 ] [ END-ACCEPT ]

The  ${\tt FROM\ CRT},\ {\tt MODE\ IS\ BLOCK\ and\ CONVERSION\ clauses}$  are syntactically recognized but are otherwise non-functional.

This format of the ACCEPT statement is used to retrieve data from a working storate item or a formatted console window screen.

1. The reserved words AFTER, IS, NUMBER and ON are optional and may be omitted. The

- presence or absence of these words has no effect upon the program.
- 2. The reserved words  ${\tt COLUMN}, {\tt COL}$  and  ${\tt POSITION}$  are interchangeable.
- 3. The reserved words TIMEOUT and TIME-OUT are interchangeable.
- 4. If identifier-1 is defined in the SCREEN SECTION (see [SCREEN SECTION], page 131), any AT, Attribute-Specification, LOWER, UPPER or SCROLL clauses will be ignored. In these cases, an implied DISPLAY (see [DISPLAY data-item], page 268) of identifier-1 will occur before input is accepted. Coding an explicit DISPLAY identifier-1 before an ACCEPT identifier-1 is redundant and will incur the performance penalty of painting the screen contents twice.
- 5. The various AT clauses provide a means of positioning the cursor to a specific spot on the screen before the screen is read. One or the other (but not both) may be used, as follows:
  - A. The LINE and COLUMN clauses provide one mechanism for specifying the line and column position to which the cursor will be positioned before allowing the user to enter data. In the absence of one or the other, a value of 1 will be assumed for the one that is missing. The author's personal preference, however, is to explicitly code both.
  - B. The *literal-3* or *identifier-4* value, if specified, must be a four- or six-digit value with the 1<sup>st</sup> half of the number indicating the line where the cursor should be positioned and the second half indicating the column. You may code only one of each clause on any ACCEPT.
- 6. WITH options (including the various individual Attribute-Specifications) should be coded only once.
- 7. The following Attribute-Specification clauses are allowed on the ACCEPT statement; these are the same as those allowed for SCREEN SECTION data items. A particular Attribute-Specification may be used only once in any ACCEPT:
  - AUTO (see [AUTO], page 141), AUTO-SKIP (see [AUTO-SKIP], page 142), AUTOTERMINATE (see [AUTOTERMINATE], page 143), TAB
  - $\bullet$  BACKGROUND-COLOR (see [BACKGROUND-COLOR], page 144)
  - BEEP (see [BEEP], page 146), BELL (see [BELL], page 147)
  - BLINK (see [BLINK], page 150)
  - FOREGROUND-COLOR (see [FOREGROUND-COLOR], page 158)
  - FULL (see [FULL], page 160), LENGTH-CHECK (see [LENGTH-CHECK], page 166)
  - HIGHLIGHT (see [HIGHLIGHT], page 163)
  - LEFTLINE (see [LEFTLINE], page 165)
  - LOWLIGHT (see [LOWLIGHT], page 169)
  - OVERLINE (see [OVERLINE], page 175)
  - PROMPT (see [PROMPT], page 183)
  - PROTECTED (see [PROTECTED], page 184)
  - REQUIRED (see [REQUIRED], page 187), EMPTY-CHECK (see [EMPTY-CHECK], page 154)
  - REVERSE-VIDEO (see [REVERSE-VIDEO], page 188)
  - SECURE (see [SECURE], page 189), NO-ECHO (see [NO-ECHO], page 171)
  - UNDERLINE (see [UNDERLINE], page 197)
- 8. The SCROLL option will cause the entire contents of the screen to be scrolled UP or DOWN by the specified number of lines before any value is displayed on the screen. It is syntactically allowable to specify a SCROLL UP clause as well as a SCROLL DOWN clause. In such an instance,

- it is the last one specified that will be honoured. If no LINES specification is made, 1 LINE will be assumed.
- 9. The TIMEOUT option will cause the ACCEPT to wait no more than the specified number of seconds for input. The wait count may be specified as a positive integer or a numeric data item with a positive value.
- 10. The UPDATE option will enable the supplied data field to be updated having been displayed on screen prior to data being entered by overwriting, if needed. When this option is *not* used the input field is cleared prior to input and this is the default but can be changed by the use of compiler steering command -faccept-with-update that can be input when starting the compiler or included in the configuration file e.g., default.conf used when selected by default -std=default. For more information see [cobc The GnuCOBOL Compiler], page 559, option switches) and [Compiler Configuration Files], page 574.
- 11. This format of the ACCEPT statement will be terminated by any of the following events:
  - A. When the Enter key is pressed.
  - B. Expiration of the TIMEOUT timer this will be treated as if the Enter key had been pressed with no data being entered.
  - C. When a function key (Fn) is pressed.
  - D. The pressing of the PgUp or PgDn keys, if the COB\_SCREEN\_EXCEPTIONS run-time environment variable (see [Run Time Environment Variables], page 584) is set to any non-blank value.
  - E. The pressing of the Esc key if *both* the COB\_SCREEN\_ESC run-time environment variable as well as COB\_SCREEN\_EXCEPTIONS run-time environment variable are set to any non-blank value.
  - F. The pressing of the Up-arrow, Down-Arrow or PrtSc (Print Screen) keys. These keys are not detectable on Windows systems, however.
- 12. The following apply when *identifier-1* is defined in the SCREEN SECTION:
  - A. Alphanumeric data entered into *identifier-1* or any screen data item subordinate to it must be consistent with the PICTURE (see [PICTURE], page 176) clause of that item. This will be enforced at runtime by the ACCEPT statement.
  - B. If identifier-1 or any screen data item subordinate to it are defined as numeric, entered data must be acceptable as NUMVAL intrinsic function (see [NUMVAL], page 427) input (no decimal points are allowed, however). The value stored into the screen data item will be as if the input were passed to that function.
  - C. If identifier-1 or any screen data item subordinate to it are defined as numeric edited, entered data must be acceptable as NUMVAL-C intrinsic function (see [NUMVAL-C], page 428) input (again, no decimal points are allowed). The value stored into the screen data item will be as if the input were passed to that function.
- 13. The following apply when identifier-1 is not defined in the SCREEN SECTION:
  - A. Alphanumeric data entered into *identifier-1 should* be consistent with the PICTURE (see [PICTURE], page 176) clause of that item, although that will not be enforced by the ACCEPT statement. You may use Class Conditions (see [Class Conditions], page 42) after the data is accepted to enforce the data type.
  - B. If identifier-1 is defined as numeric, entered data must be acceptable as NUMVAL intrinsic function (see [NUMVAL], page 427) input (no decimal points are allowed, however). The value stored into identifier-1 will be as if the input were passed to that function.
  - C. If identifier-1 is defined as numeric edited, entered data must be acceptable as NUMVAL-C intrinsic function (see [NUMVAL-C], page 428) input (again, no decimal points are

allowed). The value stored into *identifier-1* will be as if the input were passed to that function.

14. The optional ON EXCEPTION and NOT ON EXCEPTION clauses may be used to detect and react to the failure or success, respectively, of the screen I/O attempt. See [ON EXCEPTION + NOT ON EXCEPTION], page 223, for additional information.

After this format of the ACCEPT statement is executed, the program's CRT STATUS (see [SPECIAL-NAMES], page 84) identifier will be populated with one of the following:

| $\mathbf{Code}$ | Meaning                                |
|-----------------|----------------------------------------|
| 0000            | ENTER key pressed                      |
| 1001 - 1064     | F1–F64, respectively, were pressed     |
| 2001            | PgUp was pressed                       |
| 2002            | PgDn was pressed                       |
| 2003            | Up-Arrow was pressed                   |
| 2004            | Down-Arrow was pressed                 |
| 2005            | Esc was pressed                        |
| 2006            | PrtSc (Print Screen) was pressed       |
| 2007            | Tab                                    |
| 2008            | Back Tab                               |
| 2009            | Key Left                               |
| 2010            | Key Right                              |
| 2011            | Insert Key on accept omitted           |
| 2012            | Delete Key on accept omitted           |
| 2013            | Backspace Key on accept omitted        |
| 2014            | Home Key on accept omitted             |
| 2015            | End Key on accept omitted              |
| 2040-           | 2095 Exception keys for Mouse Handling |
| 2040            | Mouse Move                             |
| 2041            | Left Pressed                           |
| 2042            | Left Released                          |
| 2043            | Left Dbl Click                         |
| 2044            | Mid Pressed                            |
| 2045            | Mid Released                           |
| 2046            | Mid Dbl Click                          |
| 2047            | Right Pressed                          |
| 2048            | Right Released                         |
| 2049            | Right Dbl Click                        |
| 2050            | Shift Move                             |
| 2051            | Shift Left Pressed                     |
| 2052            | Shift Left Released                    |
| 2053            | Shift Left Dbl Click                   |
| 2054            | Shift Mid Pressed                      |
| 2055            | Shift Mid Released                     |
| 2056-           | Shift Mid Dbl Click                    |
| 2057            | Shift Right Pressed                    |
| 2058            | Shift Right Released                   |
| 2059            | Shift Right Dbl Click                  |
| 2060            | Ctrl Move                              |
| 2061            | Ctrl Left Pressed                      |
| 2062            | Ctrl Left Released                     |

| 2063          | Ctrl Left Dbl Click                |
|---------------|------------------------------------|
| 2064          | Ctrl Mid Pressed                   |
| 2065          | Ctrl Mid Tressed Ctrl Mid Released |
| 2066          | Ctrl Mid Dbl Click                 |
| 2067          |                                    |
| 2068          | Ctrl Right Pressed                 |
| 2069          | Ctrl Right Released                |
|               | Ctrl Right Dbl Click<br>Alt Move   |
| 2070          | Alt Left Pressed                   |
| 2071          | Alt Left Released                  |
| 2072<br>2073- | Alt Left Dbl Click                 |
|               | Alt Mid Pressed                    |
| 2074          |                                    |
| 2075          | Alt Mid Released                   |
| 2076          | Alt Mid Dbl Click                  |
| 2077          | Alt Right Pressed                  |
| 2078          | Alt Right Released                 |
| 2079          | Alt Right Dbl Click                |
| 2080          | Wheel Up                           |
| 2081          | Wheel Down                         |
| 2082          | Wheel Left                         |
| 2083          | Wheel Right                        |
| 2084          | Shift Wheel Up                     |
| 2085          | Shift Wheel Down                   |
| 2086          | Shift Wheel Left                   |
| 2087          | Shift Wheel Right                  |
| 2088          | Ctrl Wheel Up                      |
| 2089          | Ctrl Wheel Down                    |
| 2090          | Ctrl Wheel Left                    |
| 2091          | Ctrl Wheel Right                   |
| 2092          | Alt Wheel Up                       |
| 2093          | Alt Wheel Down                     |
| 2094          | Alt Wheel Left                     |
| 2095          | Alt Wheel Right                    |
|               | Input validation                   |
| 8000          | NO Field                           |
| 8001          | Time Out                           |
|               | Other errors                       |
| 9000          | Fatal                              |
| 9001          | Max Field                          |
|               |                                    |

15. The actual key pressed to generate a function key (Fn) will depend on the type of terminal device you're using (PC, Macintosh, VT100, etc.) and what type of enhanced display driver was configured with the version of GnuCOBOL you're using.

For example, on a GnuCOBOL build for a Windows PC using MinGW and "PDCurses", F1–F12 are the actual F-keys on the PC keyboard, F13–F24 are entered by shifting the F-keys, F25–F36 are entered by holding Ctrl while pressing an F-key and F37–F48 are entered by holding Alt while pressing an F-key. On the other hand, a GnuCOBOL implementation built for Windows using Cygwin and NCurses treats the PCs F1–F12 keys as the actual F1–F12, while shifted F-keys will enter F11–F20. With Cygwin/NCurses, Ctrl- and Alt-modified F-keys aren't recognized, nor are Shift-F11 or Shift-F12.

Mouse Key codes are populated only if mouse management has been enabled. To enable mouse it is first necessary to set COB\_MOUSE\_FLAGS (either externally via terminal command, or internally via SET ENVIRONMENT to the applicable ?mouse mask? (specifying which activities you wish the program to detect). Here is an example of setting the mask from a COBOL program:

```
COPY screenio.cpy.

01 mouse-flags PIC 9(4).

...

COMPUTE mouse-flags = COB-AUTO-MOUSE-HANDLING + COB-ALLOW-LEFT-DOWN + COB-ALLOW-MIDDLE-DOWN + COB-ALLOW-RIGHT-DOWN

SET ENVIRONMENT "COB_MOUSE_FLAGS" TO mouse-flags.
```

16. Once that has been done, every (extended) ACCEPT, will return a value in COB\_CRT\_STATUS reflecting mouse activity, when such activity occurs. The applicable values are shown in screenio.cpy under ?Exception keys for mouse handling?. If you define a variable in SPECIAL NAMES as follows:

```
SPECIAL-NAMES.
```

CURSOR IS data-name. \*> where data-name is PIC 9(4) or 9(6).

- 17. The cursor or mouse position will be returned as well. The position is expressed as row and column (rrcc or rrrccc).
- 18. Numeric keypad keys are not recognizable on Windows MinGW/PDCurses builds of Gnu-COBOL, regardless of the number lock settings. Windows Cygwin/NCurses builds recognize numeric keypad inputs properly. Although not tested during the preparation of this documentation, I would expect native Windows builds using PDCurses to behave as MinGW builds do and native Unix builds using NCurses to behave as do Cygwin builds.
- 19. The optional EXCEPTION-STATUS clause may be used to detect exceptions from a prior arithmetic verb such as COMPUTE to recover any errors produced. These are recovered using the function EXCEPTION-STATUS.

# 7.8.1.5. ACCEPT FROM DATE/TIME

#### 

This format of the ACCEPT statement is used to retrieve the current system date, time or current day of the week and store it into a data item.

1. The data retrieved from the system and the format in which it is structured will vary, as follows:

| Syntax        | Data Retrieved                              | Format   |
|---------------|---------------------------------------------|----------|
| DATE          | Current date in Gregorian form              | yymmdd   |
| DATE YYYYMMDD | Current date in Gregorian form              | yyyymmdd |
| DAY           | Current date in Julian form                 | yyddd    |
| DAY YYYYDDD   | Current date in Julian form                 | yyyyddd  |
| TIME          | Time, including hundredths of a second (nn) | hhmmssnn |
| DAY-OF-WEEK   | Current day within a week where $1 = Mon$   | d        |
|               | day, 7 = Sunday                             |          |

# 7.8.1.6. ACCEPT FROM Screen-Info

# ACCEPT identifier-1 FROM { LINES|LINE-NUMBER } ( COLS|COLUMNS ) ( ESCAPE KEY ) END-ACCEPT ]

This format of the ACCEPT statement is used to retrieve information about the console window or about the user's interactions with it.

- 1. The reserved words LINES and LINE-NUMBER are interchangeable.
- 2. The reserved words COLS and COLUMNS are interchangeable.
- 3. The following points pertain to the use of the LINES and COLUMNS options:
  - A. The LINES and COLUMNS options will retrieve the respective components of the size of the console display.
  - B. When the console is running in a windowed environment, this will be the sizing of the window in which the program is executing, in terms of horizontal (COLUMNS) or vertical (LINES) character counts not pixels.
  - C. When the system is not running a windowing environment, the physical console screen attributes will be returned.
  - D. Values of 0 will be returned if GnuCOBOL was not generated to include screen I/O.
  - E. See the documentation on the CBL\_GET\_SCR\_SIZE built-in system subroutine (see [CBL\_GET\_SCR\_SIZE], page 518) for another way to retrieve this information.
- 4. The ESCAPE KEY option may be used after the ACCEPT FROM Screen-Info statement (see [ACCEPT FROM Screen-Info], page 241) has executed. The result returned will be the four-digit CRT STATUS (see [SPECIAL-NAMES], page 84) identifier value. See [CRT STATUS Codes], page 237, for the specific code values.

# 7.8.1.7. ACCEPT FROM Runtime-Info

#### ACCEPT FROM Runtime-Info Syntax

```
ACCEPT identifier-1

FROM { EXCEPTION STATUS }

(USER NAME)

END-ACCEPT]
```

This format of the ACCEPT statement is used to retrieve run-time information such as the most-recent error exception code and the current user's user name.

- 1. The following points pertain to the use of the EXCEPTION STATUS option:
  - A. identifier-1 must be defined as a PIC X(4) item.
  - B. See [Error Exception Codes], page 384, for a complete list of the exception codes and their meanings.
  - C. An alternative to the use of ACCEPT FROM Runtime-Info is to use the EXCEPTION-STATUS intrinsic function (see [EXCEPTION-STATUS], page 384).
- 2. The following points pertain to the use of the USER NAME option:
  - A. The returned result is the userid that was used to login to the system with, and not any actual first and/or last name of the user in question (unless, of course, that is the information used as a logon id). It is not the PID or UID numbers but the name associated with the UID under \*nix based systems.
  - B. identifier-1 should be defined large enough to receive the longest user-name on the system.
  - C. If insufficient space is allocated, the returned value will be truncated.
  - D. If excess space is allocated, the returned value will be padded with spaces (to the right).

# 7.8.1.8. ACCEPT OMITTED

#### **ACCEPT OMITTED Syntax**

# ACCEPT OMITTED

~~~~~

1. For console : See 6.17.1.1 (ACCEPT FROM CONSOLE Syntax)

2. For Screen : See 6.17.1.4 (ACCEPT screen-data-item Syntax)

[ END-ACCEPT ]

This format of the ACCEPT statement will wait for a keyboard event that terminates input; function keys, or Enter/Return, among others. CRT STATUS (COB-CRT-STATUS CRT STATUS (see [SPECIAL-NAMES], page 84) if not explicitly defined) is set with the keycode, listed in copy/screenio.cpy. It also handles a few other keycode terminations not normally used to complete an extended accept.

1. The following are examples of keycodes that can be used:

COB-SCR-INSERT

COB-SCR-DELETE

COB-SCR-BACKSPACE

COB-SCR-KEY-HOME

COB-SCR-KEY-END

2. You can used extended attributes, useful for setting timeouts or positioning.

# 7.8.1.9. ACCEPT FROM EXCEPTION-STATUS

# 

This format of the ACCEPT statement will receive the status for any exceptions resulting from a previous valid verb.

1. The following is an example of usage:

```
In WS:
01 exception-status pic 9(4).
..
In PD:

ACCEPT unexpected-rounding FROM EXCEPTION-STATUS
IF unexpected-rounding NOT EQUAL "0000" THEN
DISPLAY "Unexpected rounding. Code " unexpected-rounding
UPON SYSERR
END-IF
```

#### 7.8.2. ADD

# 7.8.2.1. ADD TO

```
ADD TO Syntax
 ADD { literal-1
 }...
 ~~~ { identifier-1 }
     TO { identifier-2
       [ ROUNDED [ MODE IS { AWAY-FROM-ZERO
                 } ] ] }...
                         { NEAREST-AWAY-FROM-ZERO }
                         { ~~~~~~~~~~
                         { NEAREST-EVEN
                           ~~~~~~~~~~~
 }
 { NEAREST-TOWARD-ZERO
 {
 }
 { PROHIBITED
 }
 { ~~~~~~
 }
 { TOWARD-GREATER
                           ~~~~~~~~~~~~~
                                               }
                         {
                         { TOWARD-LESSER
                                               }
                         {
                                               }
                         { TRUNCATION
   [ ON SIZE ERROR imperative-statement-1 ]
   [ NOT ON SIZE ERROR imperative-statement-2 ]
[ END-ADD ]
```

This format of the ADD statement generates an intermediate arithmetic sum of the values of all identifier-1 and literal-1) items. The value of each identifier-2 will be replaced, in turn, by the sum of that identifier-2s value and the intermediate sum.

- 1. The reserved words IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. Both identifier-1 and identifier-2 must be numeric unedited data items while literal-1 must be a numeric literal.
- 3. An *identifier-1* data item may also be coded as an *identifier-2*. Note, however, that the value of such a data item will therefore be included *twice* in the result.
- 4. The contents of each identifier-1 will remain unchanged by this statement.
- 5. The optional ROUNDED (see [ROUNDED], page 224) clause available to each *identifier-2* will control how non-integer results will be saved.
- 6. The optional ON SIZE ERROR and NOT ON SIZE ERROR clauses may be used to detect and react to the failure or success, respectively, of an attempt to perform a calculation. In this

case, failure is defined as being an *identifier-2* with an insufficient number of digit positions available to the left of any implied decimal point. See [ON SIZE ERROR + NOT ON SIZE ERROR], page 223, for additional information.

#### 7.8.2.2. ADD GIVING

#### ADD GIVING Syntax

```
ADD { literal-1
 ~~~ { identifier-1 }
 [TO identifier-2]
 GIVING { identifier-3
 [ROUNDED [MODE IS { AWAY-FROM-ZERO
 }]] }...
 { NEAREST-AWAY-FROM-ZERO }
 { NEAREST-EVEN
 }
 }
 { NEAREST-TOWARD-ZERO
 { ~~~~~~~~~
 }
 { PROHIBITED
 }
 { ~~~~~~~
 }
 { TOWARD-GREATER
 }
 }
 }
 { TOWARD-LESSER
 { ~~~~~~~
 }
 { TRUNCATION
 }
 [ON SIZE ERROR imperative-statement-1]
 [NOT ON SIZE ERROR imperative-statement-2]
[END-ADD]
```

This format of the ADD statement generates the arithmetic sum of the values of all identifier-1, literal-1) and identifier-2 (if any) items and then saves that sum to each identifier-3.

- 1. The reserved words IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. Both identifier-1 and identifier-2 must be numeric unedited data items while literal-1 must be a numeric literal; identifier-3 may be either a numeric or numeric edited data item.
- 3. An identifier-1 or identifier-2 data item may be used as an identifier-3, if desired.
- 4. The contents of each *identifier-1* and *identifier-2* will remain unchanged by this statement, unless they happen to also be specified as an *identifier-3*.
- 5. The current value in each *identifier-3* at the start of the statement's execution is irrelevant, since the contents of each *identifier-3* will simply be replaced with the computed sum.
- 6. The optional ROUNDED (see [ROUNDED], page 224) clause available to each identifier-3 will control how non-integer results will be saved.

7. The optional ON SIZE ERROR and NOT ON SIZE ERROR clauses may be used to detect and react to the failure or success, respectively, of an attempt to perform a calculation. In this case, failure is defined as being an *identifier-3* with an insufficient number of digit positions available to the left of any implied decimal point. See [ON SIZE ERROR + NOT ON SIZE ERROR], page 223, for additional information.

#### 7.8.2.3. ADD CORRESPONDING

#### ADD CORRESPONDING Syntax

```
ADD CORRESPONDING identifier-1
 TO identifier-2
 }]]
 [ROUNDED [MODE IS { AWAY-FROM-ZERO
 { ~~~~~~~~
 { NEAREST-AWAY-FROM-ZERO }
 { NEAREST-EVEN
                        ~~~~~~~~~~~
                      { NEAREST-TOWARD-ZERO
                        {
                                              }
                      { PROHIBITED
                                              }
                      { TOWARD-GREATER
                                              }
                        ~~~~~~~~~~~~~~
 }
 { TOWARD-LESSER
 }
 {
 }
 { TRUNCATION
 [ON SIZE ERROR imperative-statement-1]
        ~~~~ ~~~~
   [ NOT ON SIZE ERROR imperative-statement-2 ]
[ END-ADD ]
```

This format of the ADD statement generates code equivalent to individual ADD TO (see [ADD TO], page 245) statements for corresponding matches of data items found subordinate to the two identifiers.

- 1. The reserved words IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. Both identifier-1 and identifier-2 must be group items.
- 3. See [CORRESPONDING], page 221, for information on how corresponding matches will be found between identifier-1 and identifier-2.
- 4. The optional ROUNDED (see [ROUNDED], page 224) clause available to each identifier-3 will control how non-integer results will be saved.
- 5. The optional ON SIZE ERROR and NOT ON SIZE ERROR clauses may be used to detect and react to the failure or success, respectively, of an attempt to perform a calculation. In this case, failure is defined as being an *identifier-3* with an insufficient number of digit positions available to the left of any implied decimal point. See [ON SIZE ERROR + NOT ON SIZE ERROR], page 223, for additional information.

#### **7.8.3. ALLOCATE**

#### **ALLOCATE Syntax**

FORMAT 2. ALLOCATE a memory block.

FORMAT 1. ALLOCATE a "BASED" ITEM.

The ALLOCATE statement is used to dynamically allocate memory at run-time.

- 1. The reserved words INITIALIZED and INITIALISED are interchangeable.
- 2. If data-name-1 is specified, the RETURNING phrase may be omitted; otherwise, the RETURNING phrase shall be specified.
- 3. If used, expression-1 must be an arithmetic expression with a non-zero positive integer value and the RETURNING phrase must be specified.
- 4. If used, *identifier-1* should be an 01-level item defined in working-storage or local-storage with the BASED (see [BASED], page 145) attribute. It may be an 01 item defined in the linkage section without the BASED attribute, but using such a data item is not recommended.
- 5. If used, identifier-3 should be a POINTER (see [USAGE], page 198) data item.
- 6. The optional RETURNING clause will return the address of the allocated memory block into the specified USAGE POINTER *identifier-3* data item. When this option is used, knowledge of the originally-requested size of the allocated memory block will be retained by the program in case a FREE (see [FREE], page 285) statement is ever issued against *identifier-3*.
- 7. When the *identifier-1* option is used in conjunction with INITIALIZED (or its internationalized alternative INITIALISED), the allocated memory block will be initialized as if an INITIALIZE *identifier-1* WITH FILLER ALL TO VALUE THEN TO DEFAULT (see [INITIALIZE], page 292) were executed.
- 8. When the expression-1 CHARACTERS option is used, INITIALIZED will initialize the allocated memory block to binary zeros. If INITIALIZED is not used, the initial contents of allocated memory will be left to whatever rules of memory allocation are in effect for the operating system the program is running under.

9. There are two basic ways in which this statement is used. The simplest is:

ALLOCATE My-01-Item

With this form, a block of storage equal in size to the defined size of My-01-Item (which must have been defined with the BASED attribute) will be allocated. The address of that block of storage will become the base address of My-01-Item so that it and its subordinate data items become usable within the program.

A second (and equivalent) approach is:

ALLOCATE LENGTH OF My-01-Item CHARACTERS RETURNING The-Pointer SET ADDRESS OF My-01-Item TO The-Pointer

- 10. With this form My-01-Item can either be defined with the BASED attribute or be defined in LINKAGE SECTION. Instead of LENGTH OF My-01-Item you may also use a size smaller to the maximum field size as long as you ensure that the complete field is never used.
- 11. Referencing a BASED data item either before its storage has been allocated or after its storage has been released (via the FREE statement) will lead to "unpredictable results". That's how reference manuals and standards specifications talk about this situation. In the author's experience, the results are all too predictable: the program aborts from an attempt to reference an unallocated area of memory.

# 7.8.4. ALTER

#### **ALTER Syntax**

ALTER procedure-name-1 TO PROCEED TO procedure-name-2

The ALTER statement was used in the early years of the COBOL language to edit the object code of a program at execution time, changing a GO TO (see [Simple GO TO], page 288) statement

to branch to a spot in the program different than where the GO TO statement was originally compiled for.

1. The reserved words PROCEED and TO (the one *after* PROCEED) are optional and may be omitted. The presence or absence of these words has no effect upon the program.

- 2. procedure-name-1 must contain only a single statement, and that statement must be a simple GO TO.
- 3. The effect of this statement will be as if the generated machine-language code for the GO TO statement in *procedure-name-1* is changed so that the GO TO statement now transfers control to *procedure-name-2*, rather than to whatever procedure name was specified in the program source code.
- 4. Support for the ALTER verb has been added to GnuCOBOL for the purpose of enabling GnuCOBOL to pass those National Institute of Standards and Technology (NIST) tests for the COBOL programming language that require support for ALTER.
- 5. Because of the catastrophic effect this statement has on program readability and therefore the programmer's ability to debug problems with program logic, the use of ALTER in new programs is STRONGLY discouraged.

#### 7.8.5. CALL

```
CALL Syntax
 CALL [ { STDCALL
                         } ] { literal-1
       { ~~~~~
                         }
                            { identifier-1 }
        { STATIC
                         }
        { ~~~~~
                         }
        { mnemonic-name-1 }
      [ USING CALL-Argument...
      [ RETURNING|GIVING identifier-2 ]
        [ ON OVERFLOW|EXCEPTION imperative-statement-1 ]
           ~~~~~~~
 [NOT ON OVERFLOW|EXCEPTION imperative-statement-2]
[END-CALL]
```

#### **CALL Argument Syntax**

```
[BY { REFERENCE }]
 { ~~~~~ }
 { CONTENT
 }
 { ~~~~~
 }
 { VALUE
 }
    ~~~~
                                             }
   { OMITTED
                                             }
   { ~~~~
                             } { identifier-2 }
                    { DEFAULT
                             }
                     { ~~~~~
                     { integer-1 }
```

The CALL statement is used to transfer control to a subroutine. See [Sub-Programming], page 603, for the specifics of using subprograms with GnuCOBOL programs.

- 1. The reserved words BY, IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved words EXCEPTION and OVERFLOW are interchangeable.
- 3. The reserved words GIVING and RETURNING are interchangeable.
- 4. The expectation is that the subroutine will eventually return control back to the calling program, at which point the CALLing program will resume execution starting with the

statement immediately following the CALL. Subprograms are not required to return to their callers, however, and are free to halt program execution if they wish.

5. The *mnemonic-name-1* / STATIC / STDCALL option, if used, affects the linkage conventions that will be used to the subroutine being called, as follows:

STATIC

causes the linkage to the subroutine to be performed in such a way as to require the subroutine to be statically-linked with the calling program. Note that this enables static-linking to be used on a subroutine-by-subroutine selective basis.

STDCALL

allows system standard calling conventions (as opposed to GnuCOBOL calling conventions) to be used when calling a subroutine. The definition of what constitutes "system standard" may vary from operating system to operating system. Use of this requires special knowledge about the linkage requirements of subroutines you are intending to CALL. Subroutines written in GnuCOBOL do not need this option.

#### mnemonic-name-1

allows a custom defined calling convention to be used. Such mnemonic names are defined using the CALL-CONVENTION (see [SPECIAL-NAMES], page 84) clause. That clause associates a decimal integer value with *mnemonic-name-1* such that the individual bits set on or off in the binary equivalent of the integer affect linkage to the subroutine as described in the following chart. Those rows of the chart marked with a "No" in the **Supported** column represent bit positions (switch settings) in the integer value that are currently accepted (to provide compatibility to other COBOL implementations) if coded, but are otherwise unsupported.

Note that bit 0 is the right-most bit in the binary value.

| <b>Bit</b> 0 | Supported<br>No | Meaning if 0 Arguments will be passed in right-to-left sequence                                                                                                                                                                                     | Meaning if 1 Arguments will be passed in left-to-right sequence.                                                     |
|--------------|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------|
| 1            | No              | The calling program will flush processed arguments from the argument stack.                                                                                                                                                                         | The called program (subroutine) will flush processed arguments from the argument stack.                              |
| 2            | Yes             | The RETURN-CODE special register (see [Special Registers], page 227) will be updated in addition to any RETURNING or GIVING data item.                                                                                                              | The RETURN-CODE special register will not be updated (but any RETURNING or GIVING data item still will).             |
| 3            | Yes             | If CALL literal is used, the subroutine will be located and linked in with the calling program at compile time or may be dynamically located and loaded at execution time, depending on compiler switch settings and operating system capabilities. | If CALL literal is used, the subroutine can only be located and linked with the calling program at compilation time. |

| 4 | No  | OS/2 "OPTLINK" conven-      | OS/2 "OPTLINK" conven-        |
|---|-----|-----------------------------|-------------------------------|
|   |     | tions will not be used to   | tions will be used to CALL    |
|   |     | CALL the subprogram.        | the subprogram.               |
| 5 | No  | Windows 16-bit "thunking"   | Windows 16-bit "thunking"     |
|   |     | will not be in effect.      | will be used to call the sub- |
|   |     |                             | routine as a DLL.             |
| 6 | Yes | The STDCALL convention will | The STDCALL convention, re-   |
|   |     | not be used.                | quired to use the Microsoft   |
|   |     |                             | Win32 API, will be used.      |

Using the STATIC option on a CALL statement is equivalent to using CALL-CONVENTION 8 (only bit 3 set).

Using the STDCALL option on a CALL statement is equivalent to using CALL CONVENTION 64 (only bit 6 set).

- 6. The value of literal-1 or identifier-1 is the entry-point of the subprogram you wish to call.
- 7. When you call a subroutine using *identifier-1*, you are forcing the runtime system to call a dynamically-loadable subprogram. The contents of *identifier-1* will be the entry-point name within that module. If this is the *first* call to any entry-point within the module being made at run-time, the contents of *identifier-1* must be the primary entry-point name of the module (which must also match the filename, minus any OS-mandated extension) of the executable file comprising the module).
- 8. You can force the GnuCOBOL runtime system to pre-load all dynamically-loaded modules that could ever be called by the program, at the time the program starts executing. This is accomplished through the use of the COB_PRE_LOAD run-time environment variable (see [Run Time Environment Variables], page 584). If used, this will only pre-load those modules invoked via CALL literal-1, as the runtime contents of identifier-1 cannot be predicted.
- 9. If the subprogram being called is a GnuCOBOL program, and if that program had the INITIAL (see [IDENTIFICATION DIVISION], page 77) attribute specified on its PROGRAM-ID clause, all of the subprogram's data division data will be restored to its initial state each time the subprogram is executed, regardless of which entry-point within the subprogram is being referenced.
  - This [re]-initialization behaviour will *always* apply to any subprogram's local-storage (if any), regardless of the use (or not) of INITIAL.
- 10. The USING clause defines a list of arguments that may be passed from the calling program to the subprogram. The manner in which any given argument is passed to the subroutine depends upon the BY clause (if any) coded (or implied) for that argument, as follows:

#### BY REFERENCE

passes the *address* of the argument to the subprogram. If the subprogram changes the contents of that argument, the change will be "visible" to the calling program.

#### BY CONTENT

passes the *address* of a *copy* of the argument to the subprogram. If the subprogram changes the value of such an argument, the change only affects the copy back in the calling program, not the original version.

BY VALUE passes the actual numeric value of the literal or identifiers contents as the argument. This feature exists to provide compatibility with C, C++ and other languages and would not normally be used when calling GnuCOBOL subprograms. Only numeric literals or numeric data items should be passed in this manner.

- If an argument lacks a BY clause, the most-recently encountered BY specification on that CALL statement will be assumed. If the first argument specified on a CALL lacks a BY clause, BY REFERENCE will be assumed.
- 11. No more than 251 arguments may be passed to a subroutine, unless the GnuCOBOL compiler was built with a specifically different argument limit specified for it. If you have access to the GnuCOBOL source code, you may adjust this limit by changing the value of the COB_MAX_FIELD_PARAMS in the call.c file (found in the libcob folder) as well as the last shown #if MAX_CALL_FIELD_PARAMS statement before you run make to build the compiler and run-time library.
- 12. The RETURNING clause allows you to specify a numeric data item into which the subroutine should return a numeric value. If you use this clause on the CALL, the subroutine should include a RETURNING (see [PROCEDURE DIVISION RETURNING], page 216) clause on its procedure division header. Of course, a subroutine may pass a value of any kind back in any argument passed BY REFERENCE.
- 13. The optional ON OVERFLOW and NOT ON OVERFLOW clauses (or ON EXCEPTION and NOT ON EXCEPTION they are interchangeable) may be used to detect and react to the failure or success, respectively, of an attempt to CALL the subroutine. Failure, in this context, is defined as the inability to either locate or load the object code of the subroutine at execution time. See [ON OVERFLOW + NOT ON OVERFLOW], page 223, for additional information.
- 14. Call also supports using an entry point stored in a PROGRAM-POINTER, avoiding the dynamic runtime lookup. GnuCOBOL keeps a cache of lookups during a program run. Repeated use of a named function does not suffer much penalty, but PROGRAM-POINTER will be just that little bit faster. To set a PROGRAM-POINTER use SET program-reference TO ENTRY "name" (or get the address from an API, and take part in callback programming).
- 15. An extension of CALL allows a call to a *Program-Pointer-1* which is preset using SET *program-pointer-1* TO ENTRY x. Additional the RETURNING clause may return a data pointer or a PROGRAM-POINTER

# **7.8.6. CANCEL**

```
CANCEL Syntax

CANCEL { literal-1 }...

~~~~~~ { identifier-1 }
```

The CANCEL statement unloads the dynamically-loadable subprogram module containing the entry-point specified as *literal-1* or *identifier-1* from memory.

- 1. If a dynamically-loadable module unloaded by the CANCEL statement is subsequently reexecuted, all data division storage for that module will once again be in its initial state.
- 2. Whether the CANCEL statement actually physically unloads a dynamically-loaded module or simply marks it as logically-unloaded depends on the use and value of the COB_PHYSICAL_CANCEL run-time environment variable (see [Run Time Environment Variables], page 584).

# 7.8.7. CLOSE

```
CLOSE Syntax

CLOSE { file-name-1 [{ REEL|UNIT [FOR REMOVAL] }] } ...

{ ~~~~~~~~~~~~ }

{ WITH LOCK }

{ ~~~~~~~~~~ }

{ WITH NO REWIND }
```

The REEL, LOCK and NO REWIND clauses are syntactically recognized but are otherwise non-functional, except for the CLOSE...NO REWIND statement, which will generate a file status of 07 rather than the usual 00 (but take no other action).

The CLOSE statement terminates the program's access to the specified file(s).

- 1. The reserved words FOR and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved words REEL and UNIT are interchangeable.
- 3. The CLOSE statement may only be executed against files that have been successfully opened.
- 4. A successful CLOSE will write any remaining unwritten record buffers to the file (similar to an UNLOCK statement (see [UNLOCK], page 355)) and release any file locks for the file, regardless of open mode. A closed file will then be no longer available for subsequent I/O statements until it is once again OPENED.
- 5. When a ORGANIZATION LINE SEQUENTIAL (see [ORGANIZATION LINE SEQUENTIAL], page 101) or LINE ADVANCING (see [LINE ADVANCING], page 14) file is closed, a final delimiter sequence will be written to the file to signal the termination point of the final data record in the file. This will only be necessary if the final record written to the file was written with the AFTER ADVANCING (see [WRITE], page 360) option.

# 7.8.8. COMMIT

|        | COMMIT Syntax |  |
|--------|---------------|--|
| COMMIT |               |  |
|        |               |  |

The COMMIT statement performs an UNLOCK against every currently-open file, but does not close any of the files. See the UNLOCK statement (see [UNLOCK], page 355) for additional details.

#### **7.8.9. COMPUTE**

# **COMPUTE Syntax** COMPUTE { identifier-1 } ] }... [ ROUNDED [ MODE IS { AWAY-FROM-ZERO { NEAREST-AWAY-FROM-ZERO } { NEAREST-EVEN { ~~~~~~~~ { NEAREST-TOWARD-ZERO { PROHIBITED } ~~~~~~~ { } { TOWARD-GREATER } ~~~~~~~~~~~~ } } { TOWARD-LESSER { { TRUNCATION =|EQUAL arithmetic-expression-1 [ ON SIZE ERROR imperative-statement-1 ] [ NOT ON SIZE ERROR imperative-statement-2 ] [ END-COMPUTE ]

The COMPUTE statement provides a means of easily performing complex arithmetic operations with a single statement, instead of using cumbersome and possibly confusing sequences of ADD, SUBTRACT, MULTIPLY and DIVIDE statements. COMPUTE also allows the use of exponentiation — an arithmetic operation for which no other statement exists in COBOL.

- 1. The reserved words IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved word EQUAL is interchangeable with the use of '='.
- 3. Each identifier-1 must be a numeric or numeric-edited data item.
- 4. The optional ROUNDED (see [ROUNDED], page 224) clause available to each identifier-1 will control how non-integer results will be saved.
- 5. See [Arithmetic Expressions], page 38, for more information on arithmetic expressions.
- 6. The optional ON SIZE ERROR and NOT ON SIZE ERROR clauses may be used to detect and react to the failure or success, respectively, of an attempt to perform a calculation. In this case, failure is defined either as having an *identifier-3* with an insufficient number of digit positions available to the left of any implied decimal point or attempting to divide by zero. See [ON SIZE ERROR + NOT ON SIZE ERROR], page 223, for additional information.

# **7.8.10. CONTINUE**

```
CONTINUE Syntax

CONTINUE

CONTINUE AFTER { literal-1 } SECONDS

CONTINUE AFTER { arithmetic-expression-1 }
```

The CONTINUE statement is a no-operation statement that may be coded anywhere an imperative statement (see [Imperative Statement], page 632) may be coded.

- 1. The CONTINUE statement has no effect on the execution of the program.
- 2. This statement (perhaps in combination with an appropriate comment or two) makes a convenient "place holder" particularly in ELSE (see [IF], page 291) or WHEN (see [EVALUATE], page 276) clauses where no code is currently expected to be needed, but a place for code to handle the conditions in question is to be reserved in case it's ever needed.
- 3. The optional extension of (AFTER) when used with the CONTINUE statement pauses execution for a specified length of time.

# 7.8.11. DELETE

#### **DELETE Syntax**

```
DELETE file-name-1 RECORD

[INVALID KEY imperative-statement-1]

[NOT INVALID KEY imperative-statement-2]

[END-DELETE]
```

The DELETE statement logically deletes a record from a COBOL file.

- 1. The reserved words KEY and RECORD are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The ORGANIZATION of file-name-1 cannot be ORGANIZATION LINE SEQUENTIAL (see [ORGANIZATION LINE SEQUENTIAL], page 101).
- 3. The file-name-1 file cannot be a sort/merge work file (a file described using a SD (see [File/Sort-Description], page 113)).
- 4. For files in the SEQUENTIAL access mode, the last input-output statement executed against file-name-1 prior to the execution of the DELETE statement must have been a successfully executed sequential-format READ statement (see [Sequential READ], page 316). That READ will therefore identify the record to be deleted.
- 5. If file-name-1 is a RELATIVE file whose ACCESS MODE (see [ORGANIZATION RELATIVE], page 103) is either RANDOM or DYNAMIC, the record to be deleted is the one whose relative record number is currently the value of the field specified as the files RELATIVE KEY in its SELECT statement.
- 6. If file-name-1 is an INDEXED file whose ACCESS MODE (see [ORGANIZATION INDEXED], page 105) is RANDOM or DYNAMIC, the record to be deleted is the one whose primary key is currently the value of the field specified as the RECORD KEY in the file's SELECT statement.
- 7. The optional INVALID KEY and NOT INVALID KEY clauses may be used to detect and react to the failure or success, respectively, of an attempt to delete a record. See [INVALID KEY + NOT INVALID KEY], page 222, for additional information.
- 8. No INVALID KEY or NOT INVALID KEY clause may be specified for a file who's ACCESS MODE IS SEQUENTIAL.

#### 7.8.12. DISPLAY

# 7.8.12.1. DISPLAY UPON device

#### **DISPLAY UPON device Syntax**

This format of the DISPLAY statement displays the specified identifier contents and/or literal values on the system output device specified via the UPON clause.

- 1. The reserved words ON and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. If no UPON clause is specified, UPON CONSOLE will be assumed. If the UPON clause is specified, mnemonic-name-1 must be one of the built-in output device names CONSOLE, PRINTER, STDERR, STDOUT, SYSERR, SYSLIST, SYSLST or SYSOUT or a mnemonic name assigned to one of those devices via the SPECIAL-NAMES (see [SPECIAL-NAMES], page 84) paragraph.

When displaying upon the STDERR or SYSERR devices or to a *mnemonic-name-1* attached to one of those two devices, the output will be written to output pipe #2, which will normally cause the output to appear in the console output window. You may, if desired, redirect that output to a file by appending 2> filename to the end of the command that executes the program. This applies to both Windows (any type) or Unix versions of GnuCOBOL.

When displaying upon the CONSOLE, PRINTER, STDOUT, SYSLIST, SYSLST or SYSOUT devices or to a mnemonic-name-1 attached to one of them, the output will be written to output pipe #1, which will normally cause the output to appear in the console output window. You may, if desired, redirect that output to a file by appending 1> filename or simply > filename to the end of the command that executes the program. This applies to both Windows (any type) or Unix versions of GnuCOBOL.

- 3. The NO ADVANCING clause, if used, will suppress the carriage-return / line-feed sequence that is normally added to the end of any console display.
- 4. The optional ON EXCEPTION and NOT ON EXCEPTION clauses may be used to detect and react to the failure or success, respectively, of an attempt to display output to the specified device. See [ON EXCEPTION + NOT ON EXCEPTION], page 223, for additional information.

# 7.8.12.2. DISPLAY UPON COMMAND-LINE

#### **DISPLAY UPON COMMAND-LINE Syntax**

This form of the DISPLAY statement may be used to specify the command-line argument number to be retrieved by a subsequent ACCEPT FROM ARGUMENT-VALUE statement (see [ACCEPT FROM COMMAND-LINE], page 231) or to specify a new value for the command-line arguments themselves.

- 1. The reserved word ON is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. By displaying a numeric integer value UPON ARGUMENT-NUMBER, you will specify which argument (by its relative number) will be retrieved by a subsequent ACCEPT FROM ARGUMENT-VALUE statement.
- 3. Executing a DISPLAY UPON COMMAND-LINE will influence subsequent ACCEPT FROM COMMAND-LINE statements (which will then return the value you displayed), but will not influence subsequent ACCEPT FROM ARGUMENT-VALUE statements these will continue to return the original program execution parameters.
- 4. The optional ON EXCEPTION and NOT ON EXCEPTION clauses may be used to detect and react to the failure or success, respectively, of an attempt to display output to the specified item. See [ON EXCEPTION + NOT ON EXCEPTION], page 223, for additional information.

#### 7.8.12.3. DISPLAY UPON ENVIRONMENT-NAME

#### DISPLAY UPON ENVIRONMENT-NAME Syntax

This form of the DISPLAY statement can be used to create or modify environment variables.

- 1. The reserved word ON is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. To create or change an environment variable will require two DISPLAY statements. The following example sets the environment variable MY_ENV_VAR to a value of 'Demonstration Value':

```
DISPLAY "MY_ENV_VAR" UPON ENVIRONMENT-NAME
DISPLAY "Demonstration Value" UPON ENVIRONMENT-VALUE
```

- 3. Environment variables created or changed from within GnuCOBOL programs will be available to any sub-shell processes spawned by that program (i.e. CALL 'SYSTEM' (see [SYSTEM], page 532)) but will not be known to the shell or console window that started the GnuCOBOL program.
- 4. Consider using SET ENVIRONMENT (see [SET ENVIRONMENT], page 330) in lieu of DISPLAY to set environment variables as it is much simpler.
- 5. The optional ON EXCEPTION and NOT ON EXCEPTION clauses may be used to detect and react to the failure or success, respectively, of an attempt to display output to the specified item. See [ON EXCEPTION + NOT ON EXCEPTION], page 223, for additional information.

#### 7.8.12.4. DISPLAY Data-Item

#### **DISPLAY Data-Item Syntax**

```
DISPLAY identifier-1 [UPON CRT|CRT-UNDER]
                       ~~~~ ~~~ ~~~~~~~
     [ AT { | LINE NUMBER { integer-1
                                                   | } ]
       ~~ { | ~~~~ { identifier-2 }
                                                   | }
          { | COLUMN|COL|POSITION|POS NUMBER { integer-2
          { identifier-3 }
          {
                                                    }
          { { integer-3 }
                                                     }
                                                     }
          { { identifier-4 }
     [ WITH [ Attribute-Specification ]...
            [ SCROLL { UP
                          } [ { integer-4
                                            } LINE|LINES ] ]
             ~~~~~ { ~~
 }
 { identifier-5 }
 { DOWN }
 [SIZE { integer-5
              ~~~~ { identifier-6 } ]
            [ NO ADVANCING ]
     [ ON EXCEPTION imperative-statement-1 ]
     [ NOT ON EXCEPTION imperative-statement-2 ]
[ END-DISPLAY ]
```

The UPON CRT, UPON CRT-UNDER and CONVERSION clauses are syntactically recognized but are otherwise non-functional. They are supported to provide compatibility with COBOL source written for other COBOL implementations.

This format of the DISPLAY statement presents data onto a formatted screen.

1. The reserved words AFTER, LINE, LINES, NUMBER and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.

- 2. The reserved words COLUMN and POSITION are interchangeable.
- 3. The reserved words LINE and LINES are interchangeable.
- 4. If identifier-1 is defined in the SCREEN SECTION (see [SCREEN SECTION], page 131), any AT, Attribute-Specification and WITH clauses will be ignored. All field definition, cursor positioning and screen control will occur as a result of the screen section definition of identifier-1.
- 5. The following points apply if *identifier-1* is not defined in the screen section:
  - A. The purpose of the AT clause is to define where on the screen *identifier-1* should be displayed. See [ACCEPT data-item], page 234, for additional information.

- B. The purpose of the WITH clause is to define the visual attributes that should be applied to *identifier-1* when it is displayed on the screen as well as other presentation-control characteristics.
- C. The following Attribute-Specification clauses are allowed on the DISPLAY statement—these are the same as those allowed for SCREEN SECTION data items. A particular Attribute-Specification may be used only once in any DISPLAY:
  - BACKGROUND-COLOR (see [BACKGROUND-COLOR], page 144)
  - BEEP (see [BEEP], page 146), BELL (see [BELL], page 147)
  - BLANK (see [BLANK], page 148)
  - BLINK (see [BLINK], page 150)
  - ERASE (see [ERASE], page 155)
  - FOREGROUND-COLOR (see [FOREGROUND-COLOR], page 158)
  - HIGHLIGHT (see [HIGHLIGHT], page 163)
  - LOWLIGHT (see [LOWLIGHT], page 169)
  - OVERLINE (see [OVERLINE], page 175)
  - REVERSE-VIDEO (see [REVERSE-VIDEO], page 188)
  - UNDERLINE (see [UNDERLINE], page 197)
- D. See [ACCEPT data-item], page 234, for additional information on the other WITH clause options.
- 6. The optional ON EXCEPTION and NOT ON EXCEPTION clauses may be used to detect and react to the failure or success, respectively, of the screen I/O attempt. See [ON EXCEPTION + NOT ON EXCEPTION], page 223, for additional information.

When DISPLAY is used with Line and column where multiple variables or literals are used before LINE only the first will be displayed.

If this is needed then the use of CONCATENATE to built more than one element together prior to the display, e.g., DISPLAY FUNCTION CONCATENATE (VARS-1 VARS-2) AT 0201.

When DISPLAY is used without line or column controls only one variable or literal may will appear on a line, so the use of the above example should also be employed.

# 7.8.12.5. DISPLAY data-item

#### DISPLAY data-item Syntax

```
DISPLAY [position-spec] {identifier-2 | literal-1} ...
  [ WITH [ Attribute-Specification ]...
         [ ERASE { SCREEN|LINE } ]
         [ SCROLL { UP } [ { integer-3 } LINE|LINES ] ]
          ~~~~~ { ~~ } { identifier-3 }
 { DOWN }
 [SIZE { integer-4 }
          ~~~~ { identifier-4 } ]
[ END-DISPLAY ]
 where position-spec is
  { (position-spec-num, position-spec-num) }
  { (,position-spec-num)
                                         }
  { (position-spec-num,)
                                         }
 where position-spec-num is
  { identifier-1 } [{ + } integer-1 ]
  { integer-2 } [{ - }
```

This format of the DISPLAY statement presents data onto a formatted screen using the Microsoft format from v1 and v2 compilers (MsDos).

# 7.8.13. DIVIDE 7.8.13.1. DIVIDE INTO

# **DIVIDE INTO Syntax** DIVIDE { literal-1 } INTO { literal-2 } GIVING { identifier-3 ~~~~ { identifier-1 } ~~~~ { identifier-2 } ~~~~~ [ ROUNDED [ MODE IS { AWAY-FROM-ZERO } ] ] }... { ~~~~~~~~ { NEAREST-AWAY-FROM-ZERO } { NEAREST-EVEN { ~~~~~~~~ { NEAREST-TOWARD-ZERO { ~~~~~~~~~~~~~~ { PROHIBITED { ~~~~~~~~ { TOWARD-GREATER } { TOWARD-LESSER { ~~~~~~~ { TRUNCATION ~~~~~~~~~ [ REMAINDER identifier-4 ] [ ON SIZE ERROR imperative-statement-1 ] [ NOT ON SIZE ERROR imperative-statement-2 ]

For further clarification, the following examples are provided to be used with the various flavours of the DIVIDE statement when using BY, INTO and GIVING.

|                                      |         | L   | <b></b>      | L+                |
|--------------------------------------|---------|-----|--------------|-------------------|
|                                      | A       | В   | l C          | D                 |
|                                      | A       | B/A | I            | l I               |
|                                      | A       | В   | B/A          | l I               |
|                                      | A       | В   | A/B          | l I               |
| DIVIDE A INTO B GIVING C REMAINDER D | A       | l B | Integer(B/A) | Integer remainder |
|                                      | <b></b> | +   | -<br>+       | -<br>+            |

[ END-DIVIDE ]

This format of the DIVIDE statement will divide a numeric value (specified as a literal or numeric data item) into another numeric value (also specified as a literal or numeric data item) and will then replace the contents of one or more receiving data items with the results of that division.

- 1. The reserved words IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. Both identifier-1 and identifier-2 must be numeric unedited data items and literal-1 must be a numeric literal.
- 3. A division operation will be performed for each *identifier-2*, in turn. Each of the results of those divisions will be saved to the corresponding *identifier-2* data item(s).
- 4. Should any *identifier-2* be an integer numeric data item, the result computed when that *identifier-2* is divided by *literal-1* or *identifier-1* will also be an integer any remainder from that division will be discarded.
- 5. The optional ROUNDED (see [ROUNDED], page 224) clause available to each *identifier-2* will control how non-integer results will be saved.
- 6. The optional ON SIZE ERROR and NOT ON SIZE ERROR clauses may be used to detect and react to the failure or success, respectively, of an attempt to perform a calculation. In this case, failure is defined as being numeric truncation caused by an *identifier-2* with an insufficient number of digit positions available to the left of any implied decimal point, or an attempt to divide by zero. See [ON SIZE ERROR + NOT ON SIZE ERROR], page 223, for additional information.

#### 7.8.13.2. DIVIDE INTO GIVING

```
DIVIDE INTO GIVING Syntax
DIVIDE { literal-1 } INTO { literal-2
                                       } GIVING { identifier-3
~~~~~ { identifier-1 } ~~~~ { identifier-2 } ~~~~~
 [ROUNDED [MODE IS { AWAY-FROM-ZERO
 }]] }...
 { ~~~~~~~~
 { NEAREST-AWAY-FROM-ZERO }
 { ~~~~~~~~~~~
 { NEAREST-EVEN
                               ~~~~~~~~~~~
                             { NEAREST-TOWARD-ZERO
                             { ~~~~~~~~~~~
                             { PROHIBITED
                                                     }
                              { TOWARD-GREATER
                               ~~~~~~~~~~~~~
 }
 }
 { TOWARD-LESSER
 }
 { TRUNCATION
 [REMAINDER identifier-4]
     ~~~~~~~
   [ ON SIZE ERROR imperative-statement-1 ]
   [ NOT ON SIZE ERROR imperative-statement-2 ]
[ END-DIVIDE ]
```

This format of the DIVIDE statement will divide one numeric value (specified as a literal or numeric data item) into another numeric value (also specified as a literal or numeric data item) and will then replace the contents of one or more receiving data items with the results of that division.

- 1. The reserved words IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. Both identifier-1 and identifier-2 must be numeric unedited data items while both identifier-3 and identifier-4 must be numeric (edited or unedited) data items.
- 3. Both literal-1 and literal-2 must be numeric literals.
- 4. If the REMAINDER clause is coded, there may be only one identifier-3 specified.
- 5. The result obtained when the value of *literal-2* or *identifier-2* is divided by the value of *literal-1* or *identifier-1* is computed; this result is then moved into each *identifier-3*, in turn, applying the rules defined by the ROUNDED (see [ROUNDED], page 224) clause (if any) for that *identifier-3* to the move.
- 6. If a REMAINDER clause is specified, the value of the one and only identifier-3 (as stated earlier, if REMAINDER is specified there may only be a single identifier-3 coded on the statement)

- after it was assigned a value according to the previous rule will be multiplied by the value of *literal-1* or *identifier-1*; that result is then subtracted from the value of *literal-2* or *identifier-2* and *that* result is the value which is moved to *identifier-4*.
- 7. The optional ON SIZE ERROR and NOT ON SIZE ERROR clauses may be used to detect and react to the failure or success, respectively, of an attempt to perform a calculation. In this case, failure is defined as being an *identifier-2* with an insufficient number of digit positions available to the left of any implied decimal point, or an attempt to divide by zero. See [ON SIZE ERROR + NOT ON SIZE ERROR], page 223, for additional information.

#### 7.8.13.3. DIVIDE BY GIVING

```
DIVIDE BY GIVING Syntax
                  } BY { literal-2 } GIVING { identifier-3
DIVIDE { literal-1
~~~~~ { identifier-1 } ~~ { identifier-2 } ~~~~~
 [ROUNDED [MODE IS { AWAY-FROM-ZERO
 }]] }...
 { ~~~~~~~~
 { NEAREST-AWAY-FROM-ZERO }
 { ~~~~~~~~~~~
 { NEAREST-EVEN
                               ~~~~~~~~~~~
                             { NEAREST-TOWARD-ZERO
                             { ~~~~~~~~~~~
                             { PROHIBITED
                                                     }
                              { TOWARD-GREATER
                               ~~~~~~~~~~~~~
 }
 }
 { TOWARD-LESSER
 }
 { TRUNCATION
 [REMAINDER identifier-4]
     ~~~~~~~
   [ ON SIZE ERROR imperative-statement-1 ]
   [ NOT ON SIZE ERROR imperative-statement-2 ]
[ END-DIVIDE ]
```

This format of the DIVIDE statement will divide one numeric value (specified as a literal or numeric data item) by another numeric value (also specified as a literal or numeric data item) and will then replace the contents of one or more receiving data items with the results of that division.

- 1. The reserved words IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. Both identifier-1 and identifier-2 must be numeric unedited data items while both identifier-3 and identifier-4 must be numeric (edited or unedited) data items.
- 3. Both literal-1 and literal-2 must be numeric literals.
- 4. If the REMAINDER clause is coded, there may be only one identifier-3 specified.
- 5. The result obtained when the value of *literal-1* or *identifier-1* is divided by the value of *literal-2* or *identifier-2* is computed; this result is then moved into each *identifier-3*, in turn, applying the rules defined by the ROUNDED (see [ROUNDED], page 224) clause (if any) for that *identifier-3* to the move.
- 6. If a REMAINDER clause is specified, the value of the one and only identifier-3 (as stated earlier, if REMAINDER is specified there may only be a single identifier-3 coded on the statement)

- after it was assigned a value according to the previous rule will be multiplied by the value of *literal-2* or *identifier-2*; that result is then subtracted from the value of *literal-1* or *identifier-1* and *that* result is the value which is moved to *identifier-4*.
- 7. The optional ON SIZE ERROR and NOT ON SIZE ERROR clauses may be used to detect and react to the failure or success, respectively, of an attempt to perform a calculation. In this case, failure is defined as being an *identifier-2* with an insufficient number of digit positions available to the left of any implied decimal point, or an attempt to divide by zero. See [ON SIZE ERROR + NOT ON SIZE ERROR], page 223, for additional information.

### 7.8.14. ENTRY

The ENTRY statement is used to define an alternate entry-point into a subroutine, along with the arguments that subroutine will be expecting.

- 1. The reserved word BY is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. You may not use an ENTRY statement in a nested subprogram, nor may you use it in any form of user-defined function.
- 3. The USING clause defines the arguments the subroutine entry-point supports. This list of arguments must match up against the USING clause of any CALL statement that will be invoking the subroutine using this entry-point.
- 4. Each ENTRY-Argument specified on the ENTRY statement must be defined in the linkage section of the subroutine in which the ENTRY statement exists.
- 5. The *literal-1* value will specify the entry-point name of the subroutine. It must be specified exactly on CALL statements (with regard to the use of upper- and lower-case letters) as it is specified on the ENTRY statement.
- 6. The meaning of REFERENCE, CONTENT and VALUE are the same as the equivalent specifications on the CALL statement (see [CALL], page 253). Whatever specification will be used for an argument on the CALL to this entry-point should match the specification used in the corresponding ENTRY-Argument. The same rules regarding the presence or absence of a BY clause on a CALL statement apply to the presence or absence of a BY clause on the corresponding argument of the ENTRY statement.

### **7.8.15. EVALUATE**

# EVALUATE Selection-Subject-1 [ ALSO Selection-Subject-2 ]... { WHEN Selection-Object-1 [ ALSO Selection-Object-2 ] }... [ imperative-statement-1 ] }... [ WHEN OTHER imperative-statement-other ] [ END-EVALUATE ]

### **EVALUATE** Selection Subject Syntax

```
{ TRUE } { ~~~~ } { ~~~~ } { FALSE } { ~~~~~ } { expression-1 } { identifier-1 } { literal-1 }
```

### **EVALUATE Selection Object Syntax**

```
{ ANY
                                                         }
{ ~~~
                                                         }
{ TRUE
 ~~~~
{ FALSE
 }
\{ partial-expression-1 \}
{
{ { expression-2 } [THRU|THROUGH { expression-3 }] }
{ { identifier-2 }
 { identifier-3 }
 }
{ { literal-2
 }
 { literal-3
 }
```

The EVALUATE statement provides a means of defining processing that should take place under any number of mutually-exclusive conditions.

- 1. The reserved words  ${\tt THRU}$  and  ${\tt THROUGH}$  are interchangeable.
- 2. There must be at least one WHEN clause (in addition to any WHEN OTHER clause) specified on any EVALUATE statement.

- 3. There must be at least one Selection-Subject specified on the EVALUATE statement. Any number of additional Selection-Subject clauses may be specified, using the ALSO reserved word to separate each from the prior.
- 4. Each WHEN clause (other than the WHEN OTHER clause, if any) must have the same number of Selection-Object clauses as there are Selection-Subject clauses.
- 5. When using THRU, the values on both sides of the THRU must be the same class (both numeric, both alphanumeric, etc.).
- 6. A partial-expression is one of the following:
  - A. A Class Condition without a leading identifier-1 (see [Class Conditions], page 42).
  - B. A Sign Condition without a leading identifier-1 (see [Sign Conditions], page 44).
  - C. A Relation Condition with nothing to the left of the relational operator (see [Relation Conditions], page 46).
- 7. At execution time, each Selection-Subject on the EVALUATE statement will have its value matched against that of the corresponding Selection-Object on a WHEN clause, in turn, until:
  - A. A WHEN clause has each of its Selection-Object(s) successfully matched by the corresponding Selection-Subject; this will be referred to as the 'Selected WHEN clause'.
  - B. The complete list of WHEN clauses (except for the WHEN OTHER clause, if any) has been exhausted. In this case, there is no 'Selected WHEN Clause'.
- 8. If a 'Selected WHEN Clause' was identified:
  - A. The imperative-statement-1 (see [Imperative Statement], page 632) immediately following the 'Selected WHEN Clause' will be executed. If the 'Selected WHEN Clause' is lacking an imperative-statement-1, the first imperative-statement-1 found after any following WHEN clause will be executed.
  - B. Once the *imperative-statement-1* has been executed, or no *imperative-statement-1* was found anywhere after the 'Selected WHEN Clause', control will proceed to the statement following the END-EVALUATE or, if there is no END-EVALUATE, the first statement that follows the next period. If, however, the *imperative-statement-1* included a GO TO statement, and that GO TO was executed, then control will transfer to the procedure named on the GO TO instead.
- 9. If no 'Selected WHEN Clause' was identified:
  - A. The WHEN OTHER clause's *imperative-statement-other* will be executed, if such a clause was coded.
  - B. Control will then proceed to the statement following the END-EVALUATE or the first statement that follows the next period if there is no END-EVALUATE. If,however, the imperative-statement-other included a GO TO statement, and that GO TO was executed, then control will transfer to the procedure named on the GO TO instead.
- 10. In order for a Selection-Subject to match the corresponding Selection-Object on a WHEN clause, at least one of the following must be true:
  - A. The Selection-Object is ANY
  - B. The implied Relation Condition Selection-Subject = Selection Object is TRUE See [Relation Conditions], page 46, for the rules on how the comparison will be made.
  - C. The value of the Selection-Subject falls within the range of values specified by the THRU clause of the Selection-Object
  - D. If the Selection-Object is a partial-expression, then the conditional expression that would be represented by coding Selection-Subject Selection-Object evaluates to TRUE

11. Here is a sample program that illustrates the EVALUATE statement. IDENTIFICATION DIVISION. PROGRAM-ID. DEMOEVALUATE. DATA DIVISION. WORKING-STORAGE SECTION. PIC 9(1). 01 Test-Digit 88 Digit-Is-Odd VALUE 1, 3, 5, 7, 9. 88 Digit-Is-Prime VALUE 1, 3, 5, 7. PROCEDURE DIVISION. P1. PERFORM UNTIL EXIT DISPLAY "Enter a digit (0 Quits): " WITH NO ADVANCING ACCEPT Test-Digit IF Test-Digit = 0EXIT PERFORM END-IF EVALUATE Digit-Is-Odd ALSO Digit-Is-Prime WHEN TRUE ALSO FALSE DISPLAY Test-Digit " is ODD" WITH NO ADVANCING WHEN TRUE ALSO TRUE DISPLAY Test-Digit " is PRIME" WITH NO ADVANCING WHEN FALSE ALSO ANY DISPLAY Test-Digit " is EVEN" WITH NO ADVANCING END-EVALUATE EVALUATE Test-Digit WHEN < 5 DISPLAY " and it's small too" WHEN < 8 DISPLAY " and it's medium too" WHEN OTHER DISPLAY " and it's large too" END-EVALUATE END-PERFORM DISPLAY "Bye!" STOP RUN Console output when run (user input follows the colons on the prompts for input): Enter a digit (0 Quits): 1 1 is PRIME and it's small too Enter a digit (0 Quits): 2 2 is EVEN and it's small too Enter a digit (0 Quits): 3 3 is PRIME and it's small too Enter a digit (0 Quits): 4 4 is EVEN and it's small too Enter a digit (0 Quits): 5

5 is PRIME and it's medium too

Enter a digit (O Quits): 6
6 is EVEN and it's medium too
Enter a digit (O Quits): 7
7 is PRIME and it's medium too
Enter a digit (O Quits): 8
8 is EVEN and it's large too
Enter a digit (O Quits): 9
9 is ODD and it's large too
Enter a digit (O Quits): 0
Bye!

### 7.8.16. EXHIBIT

```
EXHIBIT Syntax

EXHIBIT [CHANGED] [NAMED] [position-spec] [ERASE] {identifier-1 | literal-1} ...

[UPON mnemonic-name-1]

where position-spec is

{(position-spec-num, position-spec-num)}
{(, position-spec-num) }
{(position-spec-num,) }

where position-spec-num is

{identifier-2} [{+} integer-2]
{integer-1 } [{-}]
```

The EXHIBIT statement causes an (optionally conditional) display of the literals, and/or identifiers (optionally preceded by the identifier name) specified in the statement for the purposes of debugging.

- 1. EXHIBIT is only present to ease migrations, this is an archaic language element in Gnu-COBOL (but without the archaic message warning because there is no explicit dialect configuration for that other than the reserved word). Depending on the -std used it will either compile or not. As the standard says about archaic language elements:
  - it should not be used in new compilation groups because better programming practices exist. The use of DISPLAY is more portable and allows for the same feature-set (with the exception of CHANGED which GnuCOBOL may not support for a long time and with the need of a literal for NAMED). This statement can be removed from any later version.
- 2. The reserved words NAMED, CHANGED are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 3. Each identifier specified in the EXHIBIT statement can be any class of data. TALLY and RETURN-CODE are the only special registers that can be used as identifiers.
- 4. Literals and identifiers displayed by the EXHIBIT statement are separated by a space on the displayed line.
- 5. Each literal can be any figurative constant other than ALL.
- 6. If the literal is numeric, it must be an unsigned integer.
- 7. Each execution of an EXHIBIT NAMED statement displays each identifier or literal specified, with each identifier (including any qualifiers and subscripts) followed by a "=" (equal sign) and its current value. They all appear on a single line on the order in which they appear in the statement.
- 8. Each execution of an EXHIBIT CHANGED NAMED statement displays each identifier or literal specified, with each identifier (including any qualifiers and subscripts) followed by a "=" (equal sign) and its current value. They all appear on a single line on the order in which they appear in the statement. However, the display for each identifier (name and

- value) is conditional on the value of that identifier having changed since the last execution of the current EXHIBIT statement. If one or more of the identifier values have not changed, neither the name nor the value is printed for those identifiers. If none of the identifier values has changed, and no literals are specified, no display takes place (display of a blank line is suppressed).
- 9. Each execution of an EXHIBIT CHANGED statement displays the current value of each identifier or literal specified. They all appear on a single line on the order in which they appear in the statement. However, the value display for each identifier is conditional on the value of that identifier having changed since the last execution of the current EXHIBIT statement. If one or more of the identifier values have not changed, the value for those identifiers are not printed and spaces are inserted instead. If none of the identifier values has changed, and no literals are specified, a blank line is displayed (display of a blank line is not suppressed).
- 10. Each execution of an EXHIBIT statement with neither the CHANGED nor the NAMED option displays each identifier or literal specified. They all appear on a single line in the order in which they appear in the statement.
- 11. An EXHIBIT statement is the same as an EXHIBIT NAMED statement.
- 12. ERASE is a display attribute which got into GnuCOBOL when MS-COBOL support was increased, it is not yet implemented.
- 13. The CHANGED clause is not yet implemented but recognised by GnuCOBOL.
- 14. The UPON mnemonic-name-1 clause is not yet implemented but recognised by GnuCOBOL.

### 7.8.17. EXIT

```
EXIT Syntax
EXIT [{ PROGRAM
 }]
 { ~~~~~
 }
 }
 { FUNCTION
 {
 }
 { PERFORM [CYCLE] }
 { ~~~~~
 }
 { SECTION
 }
 ₹
 }
 { PARAGRAPH
 }
```

The EXIT statement is a multi-purpose statement; it may provide a common end point for a series of procedures, exit an in-line PERFORM, paragraph or section or it may mark the logical end of a subprogram, returning control back to the calling program.

- 1. The EXIT PROGRAM statement is not legal anywhere within a user-defined function.
- 2. The EXIT FUNCTION statement cannot be used anywhere within a subroutine.
- 3. Neither EXIT PROGRAM nor EXIT FUNCTION may be used within a USE GLOBAL routine in DECLARATIVES (see [DECLARATIVES], page 218).
- 4. The following points describe the EXIT statement with none of the optional clauses:
  - A. When this form of an EXIT statement is used, it must be the only statement in the procedure (paragraph or section) in which it occurs. This is *not* enforced in GnuCOBOL.
  - B. This usage of the EXIT statement simply provides a common "GO TO" end point for a series of procedures, as may be seen in the following example:

C. In this case, the EXIT statement takes no other run-time action.

- 5. The following points apply to the EXIT PARAGRAPH and EXIT SECTION statements:
  - A. If an EXIT PARAGRAPH statement or EXIT SECTION statement resides in a paragraph within the scope of a procedural PERFORM (see [Procedural PERFORM], page 311), control will be returned back to the PERFORM for evaluation of any TIMES, VARYING and/or UNTIL clauses.
  - B. If an EXIT PARAGRAPH statement or EXIT SECTION statement resides *outside* the scope of a procedural PERFORM, control simply transfers to the first executable statement in the next paragraph (EXIT PARAGRAPH) or section (EXIT SECTION).
  - C. The following shows how the previous example could have been coded without a GO TO by utilizing an EXIT PARAGRAPH statement.

- 6. The following points apply to the EXIT PERFORM and EXIT PERFORM CYCLE statements:
  - A. The EXIT PERFORM and EXIT PERFORM CYCLE statements are intended to be used in conjunction with an in-line PERFORM statement (see [Inline PERFORM], page 313).
  - B. An EXIT PERFORM CYCLE statement will terminate the current iteration of the in-line PERFORM, giving control to any TIMES, VARYING and/or UNTIL clauses for them to determine if another cycle needs to be performed.
  - C. An EXIT PERFORM statement will terminate the in-line PERFORM outright, transferring control to the first statement following the END-PERFORM (if there is one) or to the next sentence following the PERFORM if there is no END-PERFORM.
  - D. This last example shows the final modification to the previous examples by using an in-line PERFORM along with EXIT PERFORM and EXIT PERFORM CYCLE statements:

```
PERFORM FOREVER

READ Input-File AT END

EXIT PERFORM

END-READ

IF Input-Rec of Input-File = SPACES

EXIT PERFORM CYCLE *> IGNORE BLANK RECORDS!

END-IF

<<pre>

END PERFORM

END PERFORM
```

7. The following points apply to the EXIT PROGRAM and EXIT FUNCTION statements:

- A. The EXIT PROGRAM and EXIT FUNCTION statements terminate the execution of a subroutine (i.e. a program that has been CALLed by another) or user-defined function, respectively, returning control back to the calling program.
- B. An EXIT PROGRAM statement returns control back to the statement following the CALL (see [CALL], page 253) of the subprogram. An EXIT FUNCTION statement returns control back to the processing of the statement in the calling program that invoked the user-defined function.
- C. If executed by a main program, neither the EXIT PROGRAM nor EXIT FUNCTION statements will take any action.
- D. The COBOL2002 standard has made a common extension to the COBOL language—the GOBACK statement (see [GOBACK], page 287)—a standard language element; the GOBACK statement should be strongly considered as the preferred alternative to both EXIT PROGRAM and EXIT FUNCTION for new subprograms.

### 7.8.18. FREE

```
FREE { [ADDRESS OF] identifier-1 }...
```

The FREE statement releases memory previously allocated to the program by the ALLOCATE statement (see [ALLOCATE], page 250).

- 1. The ADDRESS OF clause is optional and may be omitted. The presence or absence of this clause has no effect upon the program.
- 2. identifier-1 must have a USAGE (see [USAGE], page 198) of POINTER, or it must be an 01-level data item with the BASED (see [BASED], page 145) attribute.
- 3. If identifier-1 is a USAGE POINTER data item and it contains a valid address, the FREE statement will release the memory block the pointer references. In addition, any BASED data items that the pointer was used to provide an address for will become un-based and therefore unusable. If identifier-1 did not contain a valid address, no action will be taken.
- 4. If *identifier-1* is a BASED data item and that data item is currently based (meaning it currently has memory allocated to it), its memory is released and *identifier-1* will become un-based and therefore unusable. If *identifier-1* was not based, no action will be taken.

### **7.8.19. GENERATE**

## GENERATE Syntax GENERATE { report-name-1 } ~~~~~~~ { identifier-1 }

The GENERATE statement presents data to a report.

- 1. The following points apply when identifier-1 is specified:
  - A. identifier-1 must be the name of a DETAIL (see [RWCS Lexicon], page 537) report group.
  - B. If necessary, identifier-1 may be qualified with a report name.
  - C. The file in whose FD a REPORT clause exists for the report in which identifier-1 is a detail group must be opened for OUTPUT or EXTEND at the time the GENERATE is executed. See [OPEN], page 309, for information on file open modes.
  - D. The report in which *identifier-1* is a DETAIL group must have been successfully initiated via the INITIATE statement (see [INITIATE], page 296) and not yet terminated via the TERMINATE statement (see [TERMINATE], page 353) at the time the GENERATE is executed.
  - E. If at least one GENERATE statement of this form is executed against a report, the report is said to be a *detail report*. If no GENERATE statements of this form are executed against a report, the report is said to be a *summary report*.
- 2. The following points apply when report-name-1 is specified:
  - A. report-name-1 must be the name of a report having an RD defined for it in the report section.
  - B. There must be at least one CONTROL (see [RWCS Lexicon], page 537) group defined for report-name-1.
  - C. There cannot be more than one DETAIL group defined for report-name-1.
  - D. The file in whose FD a REPORT report-name-1 clause exists must be open for OUTPUT or EXTEND at the time the GENERATE is executed.
  - E. report-name-1 must have been successfully initiated (via INITIATE report-name-1) and not yet terminated (via TERMINATE) at the time the GENERATE is executed. See [OPEN], page 309, for information on file open modes.
  - F. The DETAIL group which is defined for report-name-1 will be processed but will not actually be presented to any report page. This will allow summary processing to take place. If all GENERATE statements are of this form, the report is said to be a summary report. If at least one GENERATE identifier-1 is executed, the report is considered to be a detail report.
- 3. When the first GENERATE statement for a report is executed, the contents of all control fields are saved so they may be referenced during the processing of subsequent GENERATE statements.
- 4. When, during the processing of a subsequent GENERATE, it is determined that a control field has changed value (ie. a control break has occurred), the appropriate control footing and control heading processing will take place and a snapshot of the current values of all control fields will again be saved.

### 7.8.20. GOBACK

The GOBACK statement is used to logically terminate an executing program.

- 1. If executed within a subprogram (i.e. a subroutine or user-defined function), GOBACK behaves like an EXIT PROGRAM or EXIT FUNCTION statement, respectively.
- 2. If executed within a main program, GOBACK will act as a STOP RUN statement.
- 3. The optional RETURNING clause provides the opportunity to return a numeric value to the operating system (technically, an *exit status* The manner in which the exit status value is interrogated by the operating system varies. Windows can use %ERRORLEVEL% to query the exit status while Unix shells such as sh, bash and ksh can query the exit status as \$?. Other Unix shells may have different ways to access the exit status.

### 7.8.21. GO TO

### 7.8.21.1. Simple GO TO

### Simple GO TO Syntax

GO TO procedure-name-1

This form of the GO TO statement unconditionally transfers control in a program to the first executable statement within the specified *procedure-name-1*.

- 1. The reserved word T0 is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. If this format of the GO TO statement appears in a consecutive sequence of imperative statements (see [Imperative Statement], page 632) within a sentence, it must be the *final* statement in the sentence.
- 3. If a GO TO is executed within the scope of...
  - A. ...an in-line PERFORM (see [PERFORM], page 311), the PERFORM is terminated as control of execution transfers to procedure-name-1.
  - B. ...a procedural PERFORM (see [PERFORM], page 311), and procedure-name-1 lies outside the scope of that PERFORM, the PERFORM is terminated as control of execution transfers to procedure-name-1.
  - C. ...a MERGE statement (see [MERGE], page 302) OUTPUT PROCEDURE or within the scope of either an INPUT PROCEDURE or OUTPUT PROCEDURE of a SORT statement (see [File-Based SORT], page 339), and procedure-name-1 lies outside the scope of that procedure, the SORT or MERGE operation is terminated as control of execution transfers to procedure-name-1. Any sorted or merged data accumulated to that point is lost.

### 7.8.21.2. GO TO DEPENDING ON

### GO TO DEPENDING ON Syntax

GO TO procedure-name-1...

DEPENDING ON identifier-1

This form of the GO TO statement will transfer control to any one of a number of specified procedure names depending on the numeric value of the identifier specified on the statement.

- 1. The reserved word T0 is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. The PICTURE (see [PICTURE], page 176) and/or USAGE (see [USAGE], page 198) of the specified *identifier-1* must be such as to define it as a numeric, unedited, preferably unsigned integer data item.
- 3. If the value of *identifier-1* has the value 1, control will be transferred to the 1st specified procedure name. If the value is 2, control will transfer to the 2nd procedure name, and so on.

If control of execution is transferred to a procedure named on the statement, and the  ${\tt GO}$   ${\tt TO}$  is executed within the scope of. . .

- A. ...an in-line PERFORM (see [PERFORM], page 311), the PERFORM is terminated as control of execution transfers to the procedure named on the statement.
- B. ...a procedural PERFORM (see [PERFORM], page 311), and procedure-name-1 lies outside the scope of that PERFORM, the PERFORM is terminated as control of execution transfers to the procedure named on the statement.
- C. ...a MERGE statement (see [MERGE], page 302) OUTPUT PROCEDURE or within the scope of either an INPUT PROCEDURE or OUTPUT PROCEDURE of a SORT statement (see [File-Based SORT], page 339), and procedure-name-1 lies outside the scope of that procedure, the SORT or MERGE operation is terminated as control of execution transfers to the procedure named on the statement. Any sorted or merged data accumulated to that point is lost.
- 4. If the value of *identifier-1* is less than 1 or exceeds the total number of procedure names specified on the statement, control will simply fall through into the next statement following the GO TO.
- 5. The following example shows how GO TO ... DEPENDING ON may be used in a real application situation, and compares it against an alternative EVALUATE (see [EVALUATE], page 276).

```
GO TO DEPENDING ON
 EVALUATE
 GO TO
 EVALUATE Acct-Type
 ACCT-TYPE-1
 WHEN 1
 ACCT-TYPE-2
 <<< Handle Acct Type 1 >>>
 ACCT-TYPE-3
 WHEN 2
 DEPENDING ON Acct-Type.
 <<< Handle Acct Type 2 >>>
 <<< Invalid Acct Type >>>
 WHEN 3
 <<< Handle Acct Type 3 >>>
 GO TO All-Done.
Acct-Type-1.
 WHEN OTHER
 <<< Handle Acct Type 1 >>>
 <<< Invalid Acct Type >>>
 GO TO All-Done.
 END-EVALUATE.
Acct-Type-2.
 <<< Handle Acct Type 2 >>>
 GO TO All-Done.
Acct-Type-3.
 <<< Handle Acct Type 3 >>>
All-Done.
```

6. Current programming philosophy would prefer the use of the EVALUATE statement to that of this form of the GO TO statement.

### 7.8.22. IF

### IF Syntax

The IF statement is used to conditionally execute an imperative statement (see [Imperative Statement], page 632) or to select one of two different imperative statements to execute based upon the TRUE/FALSE value of a conditional expression.

- 1. The reserved word THEN is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. You cannot use both NEXT SENTENCE and the END-IF scope terminator in the same IF statement.
- 3. If conditional-expression evaluates to TRUE, imperative-statement-1 will be executed regardless of whether or not an ELSE clause is present. Once imperative-statement-1 has been executed, control falls into the first statement following the END-IF or to the first statement of the next sentence if there is no END-IF clause.
- 4. If the optional ELSE clause is present and conditional-expression evaluates to false, then (and only then) *imperative-statement-2* will be executed. Once *imperative-statement-2* has been executed, control falls into the first statement following the END-IF or to the first statement of the next sentence if there is no END-IF clause.
- 5. The clause NEXT SENTENCE may be substituted for either imperative-statement, but not both. If control reaches a NEXT SENTENCE clause due to the truth or falsehood of *conditional-expression*, control will be transferred to the first statement of the next sentence found in the program (the first statement after the next period).

NEXT SENTENCE was needed for COBOL programs that were coded according to pre-1985 standards that wish to nest one IF statement inside another. See [Use of VERB/END-VERB Constructs], page 50, for an explanation of why NEXT SENTENCE was necessary.

Programs coded for 1985 (and beyond) standards don't need it, instead using the explicit scope-terminator END-IF to inform the compiler where *imperative-statement-2* (or *imperative-statement-1* if there is no ELSE clause coded) ends. New GnuCOBOL programs should be coded to use the END-IF scope terminator for IF statements. See [Use of VERB/END-VERB Constructs], page 50, for additional information.

### **7.8.23. INITIALIZE**

### **INITIALIZE Syntax**

The INITIALIZE statement initializes each *identifier-1* with certain specific values, depending upon the options specified.

- 1. The reserved words DATA, OF, THEN, TO and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved words INITIALIZE and INITIALISE are interchangeable.
- 3. The WITH FILLER, REPLACING and DEFAULT clauses are meaningful only if *identifier-1* is a group item. They are accepted if it's an elementary item, but will serve no purpose. The VALUE clause is meaningful in both cases.
- 4. A category-name-1 and/or category-name-2 may be any of the following:

### **ALPHABETIC**

The PICTURE (see [PICTURE], page 176) of the data item only contains A symbols.

### ALPHANUMERIC

The PICTURE of the data item contains only X or a combination of A and 9 symbols.

### ALPHANUMERIC-EDITED

The PICTURE of the data item contains only X or a combination of A and 9 symbols plus at least one B, O (zero) or / symbol.

### NUMERIC

The data item is one that is described with a picture less USAGE (see [USAGE], page 198) or has a PICTURE composed of nothing but P, 9, S and V symbols.

### NUMERIC-EDITED

The PICTURE of the data item contains nothing but the symbol 9 and at least one of the editing symbols , +, -, CR, DB, ., , * or Z.

### NATIONAL

The data item is one containing nothing but the N symbol.

### NATIONAL-EDITED

The data item contains nothing but N, B, / and O symbols.

- 5. From the sequence of *identifier-1* data items specified on the INITIALIZE statement, a list of initialized fields referred to as the *field list* in the remainder of this section, will include:
  - A. Every *identifier-1* that is an elementary item, including any that may have the REDEFINES (see [REDEFINES], page 185) clause in their descriptions.
  - B. Every non-FILLER 3elementary item subordinate to *identifier-1*, provided that elementary item neither contains a REDEFINES clause in its definition nor belongs to a group item *subordinate to identifier-1* which contains a REDEFINES clause in its definition.
  - C. If the optional WITH FILLER clause is included on the INITIALIZE statement, then every FILLER elementary item subordinate to each *identifier-1* will be included as well, provided that elementary item neither contains a REDEFINES clause in its definition nor belongs to a group item *subordinate to identifier-1* which contains a REDEFINES clause in its definition..
- 6. Once a field list has been determined, each item in that field list will be initialized as if an individual MOVE (see [MOVE], page 305) statement to that effect had been coded. The rules for initialization are as follows:
- 7. If no VALUE, REPLACING or DEFAULT clauses are coded, each member of the field list will be initialized as if the figurative constant ZERO (if the field list item is numeric or numeric-edited) or SPACES (otherwise) were being moved to it.
- 8. If a VALUE clause is specified on the INITIALIZE statement, each qualifying member of the field list having a compile-time VALUE (see [VALUE], page 207) specified in its definition will be initialized to that value. Field list members with VALUE clauses will qualify for this treatment as follows:
  - A. If the ALL keyword was specified on the VALUE clause, all members of the field list with VALUE clauses will qualify.
  - B. If *category-name-1* is specified instead of ALL, only those members of the field list with VALUE clauses that also meet the criteria set down for the specified *category-name* (see the list above) will qualify.
  - C. If you need to apply VALUE initialization to multiple category-name-1 values, you will need to use multiple INITIALIZE statements.
- 9. If a REPLACING clause is specified on the INITIALIZE statement, each qualifying member of the field list that was not already initialized by a VALUE clause, if any, will be initialized to the specified *literal-1* or *identifier-1* value.
  - Only those as-yet uninitialized list members meeting the criteria set forth for the specified category-name-2 will qualify for this initialization.
  - If you need to apply REPLACING initialization to multiple *category-name-2* values, you may repeat the syntax after the reserved word REPLACING, as necessary.
- 10. If a DEFAULT clause is specified, any remaining uninitialized members of the field list will be initialized according to the default for their class (numeric and numeric-edited are initialized to ZERO, all others are initialized to SPACES).
- 11. The following example may help your understanding of how the INITIALIZE statement works. The sample code makes use of the COBDUMP program to dump the storage that is (or is not) being initialized. See Section "COBDUMP" in *GnuCOBOL Sample Programs*, for a source and cross-reference listing of the COBDUMP program.

IDENTIFICATION DIVISION.

PROGRAM-ID. DemoInitialize.

```
DATA DIVISION.
WORKING-STORAGE SECTION.
01 Item-1.
 05 I1-A VALUE ALL '*'.
 PIC X(1).
 10 FILLER
 10 I1-A-1
 PIC 9(1) VALUE 9.
 05 I1-B
 USAGE BINARY-CHAR.
 05 I1-C
 PIC A(1) VALUE 'C'.
 05 I1-D
 PIC X/X VALUE 'ZZ'.
 OCCURS 2 TIMES PIC 9.
 05 I1-E
PROCEDURE DIVISION.
000-Main.
 DISPLAY "MOVE HIGH-VALUES TO Item-1"
 PERFORM 100-Init-Item-1
 CALL "COBDUMP" USING Item-1
 DISPLAY " "
 DISPLAY "INITIALIZE Item-1"
 INITIALIZE Item-1
 CALL "COBDUMP" USING Item-1
 PERFORM 100-Init-Item-1
 DISPLAY " "
 DISPLAY "INITIALIZE Item-1 WITH FILLER"
 MOVE HIGH-VALUES TO Item-1
 INITIALIZE Item-1 WITH FILLER
 CALL "COBDUMP" USING Item-1
 PERFORM 100-Init-Item-1
 DISPLAY " "
 DISPLAY "INITIALIZE Item-1 ALL TO VALUE"
 MOVE HIGH-VALUES TO Item-1
 INITIALIZE Item-1 ALPHANUMERIC TO VALUE
 CALL "COBDUMP" USING Item-1
 PERFORM 100-Init-Item-1
 DISPLAY " "
 DISPLAY "INITIALIZE Item-1 REPLACING NUMERIC BY 1"
 MOVE HIGH-VALUES TO Item-1
 INITIALIZE Item-1 REPLACING NUMERIC BY 1
 CALL "COBDUMP" USING Item-1
 PERFORM 100-Init-Item-1
 DISPLAY " "
 STOP RUN
100-Init-Item-1.
 MOVE HIGH-VALUES TO Item-1
```

INITIALIZE Item-1 REPLACING NUMERIC BY 1

00404058 1 FF 31 01 FF FF FF FF 31 31

When executed, this program produces the following output: MOVE HIGH-VALUES TO Item-1 <-Addr-> Byte <----- Hexadecimal -----> <---- Char ---> 00404058 1 FF FF FF FF FF FF FF FF INITIALIZE Item-1 <-Addr-> Byte <----- Hexadecimal -----> <--- Char ---> 00404058 1 FF 30 00 20 2F 20 30 30 INITIALIZE Item-1 WITH FILLER <-Addr-> Byte <----- Hexadecimal -----> <---- Char ---> INITIALIZE Item-1 ALL TO VALUE <-Addr-> Byte <----- Hexadecimal -----> <---- Char ---> _____ **.CZZ ..

<-Addr-> Byte <------ Hexadecimal -----> <---- Char --->

### **7.8.24. INITIATE**

### INITIATE Syntax INITIATE report-name-1

The INITIATE statement starts Report-Writer Control System (RWCS) processing for a report.

- 1. Each report-name-1 must be the name of a report having an RD (see [REPORT SECTION], page 124) defined for it.
- 2. The file in whose FD (see [File/Sort-Description], page 113) a REPORT report-name-1 clause exists must be open for OUTPUT or EXTEND at the time the INITIATE statement is executed. See [OPEN], page 309, for more information on file open modes.
- 3. The INITIATE statement will initialize all of the following for each report named on the statement:
  - All sum counters, if any, will be set to 0
  - $\bullet$  The report's LINE-COUNTER special register (see [Special Registers], page 227) will be set to 0
  - The report's PAGE-COUNTER special register will be set to 1
- 4. No report content will actually presented to the report file as a result of a successful INITIATE statement that will not occur until the first GENERATE statement (see [GENERATE], page 286) is executed.

### 7.8.25. INSPECT

```
INSPECT Syntax
 }
INSPECT { literal-1
~~~~~~ { identifier-1
       { function-reference-1 }
 [ TALLYING { identifier-2 FOR { ALL|LEADING|TRAILING { literal-2
                         ~~~ { ~~~ ~~~~~~ { identifier-3 } }
 { CHARACTERS
 [| { AFTER|BEFORE } INITIAL { literal-3
 } |] }...]
 { identifier-4 } |
 [REPLACING { { ALL|FIRST|LEADING|TRAILING { literal-4
 { { ~~~ ~~~~~ { identifier-5 } }
 { CHARACTERS
 }
 }
 BY { [ALL] literal-5 }
 { identifier-6
 [| { AFTER|BEFORE } INITIAL { literal-6 } |] }...]
 { identifier-7 } |
 [CONVERTING { { literal-7 } TO { literal-8
 { identifier-8 } ~~ { identifier-9 }
 [| { AFTER|BEFORE } INITIAL { literal-9
 { identifier-10 } |
```

The INSPECT statement is used to perform various counting and/or data-alteration operations against strings.

- 1. The reserved word INITIAL is optional and may be omitted. The presence or absence of this words has no effect upon the program.
- 2. If a CONVERTING clause is specified, neither the TALLYING nor REPLACING clauses may be used.
- 3. If either the TALLYING or REPLACING clauses are specified, the CONVERTING clause cannot be used.
- 4. If both the TALLYING and REPLACING clauses are specified, they must be specified in the order shown.
- 5. All literals and identifiers must be explicitly or implicitly defined as alphanumeric or alphabetic.
- 6. If function-reference-1 is specified, it must be an invocation of an intrinsic function that returns a *string* result. Additionally, only the TALLYING clause may be specified.
- 7. If literal-1 is specified, only the TALLYING clause may be specified.

- 8. Whichever is specified literal-1, identifier-1 or function-reference-1 that item will be referred to in the discussions that follows as the 'inspect subject'.
- 9. The three optional clauses control the operation of this statement as follows:
  - A. The CONVERTING clause replaces one or more individual characters found in the inspect subject with a different character in much the same manner as is possible with the TRANSFORM statement (see [TRANSFORM], page 354).
  - B. The REPLACING clause replaces one or more sub strings located in the inspect subject with a different, but equally-sized replacement sub string. If you need to replace a sub string with another of a different length, consider using either the SUBSTITUTE intrinsic function (see [SUBSTITUTE], page 448) or the SUBSTITUTE-CASE intrinsic function (see [SUBSTITUTE-CASE], page 449).
  - C. The TALLYING clause counts the number of occurrences of one or more strings of characters in the inspect subject.
- 10. The optional INITIAL clauses may be used to limit the range of characters in the inspect subject that the CONVERTING, REPLACING or TALLYING instruction in which they occur will apply. We call this the 'target range' of the inspect subject. The target range is defined as follows:
  - A. If there is no INITIAL clause specified, the target range is the entire inspect subject.
  - B. Either a BEFORE phrase, an AFTER phrase or both may be specified. They may be specified in any order.
  - C. The starting point of the target range will be the first character following the sub string identified by the AFTER specification. The ending point will be the last character immediately preceding the sub string identified by the BEFORE specification.
  - D. If no AFTER is specified, the first character position of the target range will be character position #1 of the inspect subject.
  - E. If no BEFORE is specified, the last character position of the target range will be the last character position of the inspect subject.
- 11. The following points apply to the use of the TALLYING clause:
  - A. While there will typically be only be a single set of counting instructions on an INSPECT:

```
INSPECT Character-String
TALLYING C-ABC FOR ALL "ABC"
```

There could be multiple counting instructions specified:

```
INSPECT Character-String
TALLYING C-ABC FOR ALL "ABC"
C-BCDE FOR ALL "BCDE"
```

When there *are* multiple instructions, the one specified first will take priority over the one specified second, (and so forth) as the INSPECT proceeds forward through the inspect subject, character-by-character.

With the above example, if the inspect subject were --ABCDEF---, the final result of the counting would be that C-ABC would be incremented by 1 while C-BCDE would be incremented only once; although the human eye clearly sees two 'BCDE' sequences, the INSPECT ... TALLYING would only "see" the second — the first would have been processed by the first (higher-priority) counting instruction.

- B. Each set of counting instructions contains the following information:
  - a. A target range, specified by the presence of an AFTER INITIAL and/or BEFORE INITIAL clause; the rules for specifying target ranges were covered previously.

b. A Target Sub string — this is a sequence of characters to be located somewhere in the inspect subject and counted. Target sub strings may be defined as a literal value (figurative constants are allowed) or by the contents of an identifier. If the target sub string is specified as a figurative constant, it will be assumed to have a length of one ('1') character. The keywords before the literal or identifier control how many target sub strings could be identified from that replacement instruction, as follows:

ALL — identifies every possible target sub string that occurs within the target range. There are three occurrences of ALL 'XX' found in aXXabbXXccXXdd.

LEADING — identifies only an occurrence of the target sub string found either at the first character position of the target range or immediately following a previously-found occurrence. There are no occurrences of LEADING 'XX' found in aXXabbXXccXXdd, but there is one occurrence of LEADING 'a' (the first character).

TRAILING — identifies only an occurrence of the target sub string found either at the very end of the target range or toward the end, followed by nothing but other occurrences. There are no occurrences of LEADING 'XX' found in aXXabbXXccXXdd, but there are two occurrences of TRAILING 'd'.

The CHARACTERS option will match any one single character, regardless of what that character is.

- C. identifier-2 will be incremented by 1 each time the target sub string is found within the target range of the inspect subject. The INSPECT statement will not zero-out identifier-2 at the start of execution of the INSPECT it is the programmer's responsibility to ensure that all identifier-2 data items are properly initialized to the desired starting values prior to execution of the INSPECT.
- 12. The following points apply to the use of the REPLACING clause:
  - A. While there will typically be only be a single set of replacement instructions on an INSPECT:

```
INSPECT Character-String
REPLACING ALL "ABC" BY "DEF"
```

There could be multiple replacement instructions:

```
INSPECT Character-String
REPLACING ALL "ABC" BY "DEF"
ALL "BCDE" BY "WXYZ"
```

When there *are* multiple replacement instructions, the one specified first will take priority over the one specified second, (and so forth) as the INSPECT proceeds forward through the inspect subject, character-by-character.

With the above example, if the inspect subject were --ABCDEF---, the final result of the replacement would be --DEFDEF----WXYZF--.

- B. Each set of replacement instructions contains the following information:
  - a. A target range, specified by the presence of an AFTER INITIAL and/or BEFORE INITIAL clause; the rules for specifying target ranges were covered previously.
  - b. A Target Sub string this is a sequence of characters to be located somewhere in the inspect subject and subsequently replaced with a new value. Target sub strings, which are specified before the BY keyword, may be defined as a literal value (figurative constants are allowed) or by the contents of an identifier. If the target sub string is specified as a figurative constant, it will be assumed to have a length of one ('1') character. The keywords before the literal or identifier control

how many target sub strings could be identified from that replacement instruction, as follows:

ALL — identifies every possible target sub string that occurs within the target range. There are three occurrences of ALL 'XX' found in aXXabbXXccXXdd.

FIRST — the first occurrence of the target sub string found within the target range. The FIRST 'XX' found in aXXabbXXccXXdd would be the one found between the 'a' and 'b' characters.

LEADING — an occurrence of the target sub string found either at the first character position of the target range or immediately following a previously-found occurrence. There are no occurrences of LEADING 'XX' found in aXXabbXXccXXdd, but there is one occurrence of LEADING 'a' (the first character).

TRAILING — an occurrence of the target sub string found either at the very end of the target range or toward the end, followed by nothing but other occurrences. There are no occurrences of LEADING 'XX' found in aXXabbXXccXXdd, but there are two occurrences of TRAILING 'd'.

The CHARACTERS option will match any one single character. When you use this option, the replacement sub string (see the next item) must be exactly one character in length.

c. A Replacement Sub string — this is the sequence of characters that should replace the target sub string. Replacement sub strings are specified after the BY keyword. They too may be specified as a literal, either with or without an ALL prefix (again, figurative constants are allowed) or the value of an identifier. If a figurative constant is coded, the ALL keyword will be assumed, even if it wasn't specified. Literals without ALL will either be truncated or padded with spaces on the right to match the length of the target sub string. Literals with ALL or figurative constants will be repeated as necessary to match the length of the target sub string. Identifiers specified as replacement sub strings must be defined with a length equal to that of the target sub string.

### 13. When both REPLACING and TALLYING are specified:

- A. The INSPECT statement will make a single pass through the sequence of characters comprising the inspect subject. As the pointer to the current inspect target character reaches a point where it falls within the explicit or implicit target ranges specified on the operational instructions of the two clauses, the actions specified by those instructions will become eligible to be taken. As the character pointer reaches a point where it falls past the end of target ranges, the instructions belonging to those target ranges will become disabled.
- B. At any point in time, there may well be multipleREPLACING and/or TALLYING operational instructions active. Only one of the TALLYING and one of the REPLACING instructions (if any) can be executed for any one character pointer position. In each case, it will be the first of the instructions in each category that produces a match with its target string specification.
- C. When both a TALLYING and a REPLACING instruction have been selected for execution, the TALLYING instruction will be executed first. This guarantees that TALLYING will compute occurrences based upon the *initial* value of the inspect subject before any replacements occur.
- 14. The following points apply to the use of the CONVERTING clause:
  - A. A CONVERTING clause performs a series of single-character substitutions against a data item in much the same manner as is possible with the TRANSFORM statement (see [TRANSFORM], page 354).

- B. Unlike the TALLYING and REPLACING clauses, both of which may have multiple operations specified, there may be only one CONVERTING operation per INSPECT.
- C. If the length of literal-7 or identifier-8 (the "from" string) exceeds the length of literal-8 or identifier-9 (the "to" string), then the "to" string will be assumed to be padded to the right with enough spaces to make it the same length as the "from" string.
- D. If the length of the "from" string is less than the length of the "to" string, then the "to" string will be truncated to the length of the "from" string.
- E. Each character, in turn, within the "from" string will be searched for in the target range of the inspect subject. Each located occurrence will be replaced by the corresponding character of the "to" string.

### 7.8.26. MERGE

### **MERGE Syntax**

```
MERGE sort-file-1
 { ON { ASCENDING } KEY identifier-1... }...
 { ~~~~~~
 }
 { DESCENDING }
 [WITH DUPLICATES IN ORDER]
 [COLLATING SEQUENCE IS alphabet-name-1]
 USING file-name-1 file-name-2...
 { OUTPUT PROCEDURE IS procedure-name-1
 }
 {
 {
 [THRU|THROUGH procedure-name-2]
 {
 }
 { GIVING file-name-3...
 {
 }
```

The DUPLICATES clause is syntactically recognized but is otherwise non-functional.

The MERGE statement merges the contents of two or more files that have each been pre-sorted on a set of specified identical keys.

- 1. The reserved words IN, IS, KEY, ON, ORDER, SEQUENCE and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved words THRU and THROUGH are interchangeable.
- 3. GnuCOBOL always behaves as if the WITH DUPLICATES IN ORDER clause is specified, even if it isn't.

While any COBOL implementation's sort or merge facilities guarantee that records with duplicate key values will be in proper sequence with regard to other records with different key values, they generally make no promises as to the resulting relative sequence of records having duplicate key values with one another.

Some COBOL implementations provide this optional clause to force their sort and merge facilities to retain duplicate key-value records in their original input sequence, relative to one another.

- 4. The sort-file-1 named on the MERGE statement must be defined using a sort description (SD (see [File/Sort-Description], page 113)). This file is referred to in the remainder of this discussion as the merge work file.
- 5. Each file-name-1, file-name-2 and file-name-3 (if specified) must reference ORGANIZATION LINE SEQUENTIAL], page 101) or ORGANIZATION SEQUENTIAL (see [ORGANIZATION SEQUENTIAL], page 100) files. These files must be defined using a file description (FD (see [File/Sort-Description], page 113)).
- 6. The identifier-1 . . . field(s) must be defined as field(s) within a record of sort-file-1.
- 7. The record descriptions of file-name-1, file-name-2, file-name-3 (if any) and sort-file-1 are assumed to be identical in layout and size. While the actual data names used for fields in

these files' records may differ, the structure of records, PICTURE (see [PICTURE], page 176) of fields, USAGE (see [USAGE], page 198) of fields, size of fields and location of fields within the records should match field-by-field across all files, at least as far as the KEY fields are concerned.

- 8. A common programming technique when using the MERGE statement is to define the records of all files involved as simple elementary items of the form 01 record-name PIC X(n). where n is the record size. The only file where records are actually described in detail would then be sort-file-1.
- 9. The following rules apply to the files named on the USING clause:
  - A. None of them may be open at the time the MERGE is executed.
  - B. Each of those files is assumed to be already sorted according to the specifications set forth on the MERGE statement's KEY clause.
  - C. No two of those files may be referenced on a SAME RECORD AREA (see [SAME RECORD AREA], page 107), SAME SORT AREA or SAME SORT-MERGE AREA statement.
- 10. The merging process is as follows:
  - A. As the MERGE statement begins execution, the first record in each of the USING files is read automatically.
  - B. As the MERGE statement executes, the current record from each of the USING files is examined and compared to each other according to the rules set forth by the KEY clause and the alphabet (see [Alphabet-Name-Clause], page 88) specified on the COLLATING SEQUENCE clause. The record that should be next in sequence will be written to the merge work file and the USING file from which that record came will be read so that its next record is available. As end-of-file conditions are reached on USING files, those files will be excluded from further processing processing continues with the remaining files until all the contents of all of them have been exhausted.
  - C. After the merge work file has been populated, the merged data will be written to each file-name-3 if the GIVING clause was specified, or will be processed by utilizing an OUTPUT PROCEDURE.
  - D. When GIVING is specified, none of the *file-name-3* files can be open at the time the MERGE statement is executed.
  - E. When an output procedure is used, the procedure(s) specified on the OUTPUT PROCEDURE clause will be invoked as if by a procedural PERFORM (see [Procedural PERFORM], page 311) statement with no VARYING, TIMES or UNTIL options specified. Merged records may be read from the merge work file one at a time within the output procedure using the RETURN (see [RETURN], page 323) statement.

A GO TO statement (see [GO TO], page 288) that transfers control out of the output procedure will terminate the MERGE statement but allows the program to continue executing from the point where the GO TO statement transferred control to. Once an output procedure has been "aborted" using a GO TO it cannot be resumed, and the contents of the merge work file are lost. You may, however, re-execute the MERGE statement itself. Using a GO TO statement to prematurely terminate a merge, or restarting a previously-cancelled merge is not considered good programming style and should be avoided.

An output procedure should be terminated in the same way a procedural PERFORM statement would be. Usually, this action will be taken once the RETURN statement indicates that all records in the merge work file have been processed, but termination could occur at *any* time — via an EXIT statement (see [EXIT], page 282) — if required.

- Neither a file-based SORT statement (see [File-Based SORT], page 339) nor another MERGE statement may be executed within the scope of the procedures comprising the output procedure unless those statements utilize a different sort or merge work file.
- F. Once the output procedure terminates, or the last *file-name-3* file has been populated with merged data, the output phase and the MERGE statement itself is complete.

### 7.8.27. MOVE

### 7.8.27.1. Simple MOVE

```
Simple MOVE Syntax

MOVE { literal-1 } TO identifier-2...

~~~~ { identifier-1 } ~~
```

The Simple MOVE statement moves a specific value to one or more receiving data items.

- 1. The MOVE statement will replace the contents of one or more receiving data items (identifier-2) with a new value the one specified by literal-1 or identifier-1.
- 2. Only numeric data can be moved to a numeric or numeric-edited *identifier-2*. A MOVE involving numeric data will perform any necessary format conversions that might be necessary due to differing USAGE (see [USAGE], page 198) specifications.
- 3. The contents of the *identifier-1* data item will not be changed, unless that same data item appears as an *identifier-2*. Note that such situations will cause a warning message to be issued by the compiler, if warning messages are enabled.

### 7.8.27.2. MOVE CORRESPONDING

### MOVE CORRESPONDING identifier-1 TO identifier-2...

MOVE CORRESPONDING Syntax

The MOVE CORRESPONDING statement similarly-named items from one group item to another.

- 1. The reserved word CORRESPONDING may be abbreviated as CORR.
- 2. Both identifier-1 and identifier-2 must be group items.
- 3. See [CORRESPONDING], page 221, for a discussion of how corresponding matches between two group items are established.
- 4. When corresponding matches are established, the effect of a MOVE CORRESPONDING on those matches will be as if a series of individual MOVEs were done one for each match.

### **7.8.28. MULTIPLY**

### 7.8.28.1. MULTIPLY BY

### **MULTIPLY BY Syntax** MULTIPLY { literal-1 } BY { identifier-2 ~~~~~~ { identifier-1 } ~~ [ ROUNDED [ MODE IS { AWAY-FROM-ZERO } ] ] }... { ~~~~~~~~ } { NEAREST-AWAY-FROM-ZERO } { ~~~~~~ } { NEAREST-EVEN } { ~~~~~~~~ } { NEAREST-TOWARD-ZERO } { PROHIBITED } } { TOWARD-GREATER } } } { TOWARD-LESSER ~~~~~~~~~~ { TRUNCATION [ ON SIZE ERROR imperative-statement-1 ] [ NOT ON SIZE ERROR imperative-statement-2 ] [ END-MULTIPLY ]

The MULTIPLY BY statement computes the product of one or more data items (identifier-2) and either a numeric literal or another data item.

- 1. The reserved words IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. Both identifier-1 and identifier-2 must be numeric un-edited data items; literal-1 must be a numeric literal.
- 3. The product of *identifier-1* or *literal-1* and each *identifier-2*, in turn, will be computed and moved to each of the *identifier-2* data items, replacing the prior contents.
- 4. The value of identifier-1 is not altered, unless that same data item appears as an identifier-2.
- 5. The optional ROUNDED (see [ROUNDED], page 224) clause available to each *identifier-2* will control how non-integer results will be saved.
- 6. The optional ON SIZE ERROR and NOT ON SIZE ERROR clauses may be used to detect and react to the failure or success, respectively, of an attempt to perform a calculation. In this case, failure is defined as being an *identifier-2* with an insufficient number of digit positions available to the left of any implied decimal point. See [ON SIZE ERROR + NOT ON SIZE ERROR], page 223, for additional information.

### 7.8.28.2. MULTIPLY GIVING

### **MULTIPLY GIVING Syntax** } BY { literal-2 MULTIPLY { literal-1 } GIVING { identifier-3 ~~~~~~ { identifier-1 } ~~ { identifier-2 } ~~~~~ } ] ] }... [ ROUNDED [ MODE IS { AWAY-FROM-ZERO { ~~~~~~~~ { NEAREST-AWAY-FROM-ZERO } { NEAREST-EVEN { ~~~~~~~ } { NEAREST-TOWARD-ZERO { ~~~~~~~~~~ } { PROHIBITED } { ~~~~~~ { TOWARD-GREATER } ~~~~~~~~~~~~~~ } } { TOWARD-LESSER } } { TRUNCATION [ ON SIZE ERROR imperative-statement-1 ] [ NOT ON SIZE ERROR imperative-statement-2 ] [ END-MULTIPLY ]

The MULTIPLY GIVING statement computes the product of two literals and/or data items and saves that result in one or more other data items.

- 1. The reserved words IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. Both identifier-1 and identifier-2 must be numeric un-edited data items; literal-1 and literal-2 must be numeric literals.
- 3. The product of *identifier-1* or *literal-1* and *identifier-2* or *literal-2* will be computed and moved to each of the *identifier-3* data items, replacing their old contents.
- 4. Neither the value of *identifier-1* nor *identifier-2* will be altered, unless either appears as an *identifier-3*.
- 5. The optional ROUNDED (see [ROUNDED], page 224) clause available to each *identifier-2* will control how non-integer results will be saved.
- 6. The optional ON SIZE ERROR and NOT ON SIZE ERROR clauses may be used to detect and react to the failure or success, respectively, of an attempt to perform a calculation. In this case, failure is defined as being an *identifier-2* with an insufficient number of digit positions available to the left of any implied decimal point. See [ON SIZE ERROR + NOT ON SIZE ERROR], page 223, for additional information.

### 7.8.29. OPEN

```
OPEN Syntax
OPEN { INPUT
               } [ SHARING WITH { ALL OTHER } ] file-name-1
      { ~~~~
                                 { ~~~
                }
                                             }
       { OUTPUT }
                                 { NO OTHER }
               }
       ( I-0
                }
                                 { READ ONLY }
       {
                }
       { EXTEND }
     [ { REVERSED
                            } ] }...
       { WITH { NO REWIND } }
       {
          { ~~ ~~~~~
                          } }
       {
              { LOCK
                          } }
```

The NO REWIND, and REVERSED clauses are syntactically recognized but are otherwise non-functional.

The OPEN statement makes one or more files described in your program available for use.

- 1. The reserved words OTHER and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The SHARING and WITH LOCK clauses may not both be specified in the same OPEN statement.
- 3. Any file defined in a GnuCOBOL program must be successfully opened before it or any of its record descriptions may be referenced on:

A CLOSE statement (see [CLOSE], page 258)

A DELETE statement (see [DELETE], page 262)

A READ statement (see [READ], page 316)

A REWRITE statement (see [REWRITE], page 324)

A START statement (see [START], page 343)

An UNLOCK statement (see [UNLOCK], page 355)

A WRITE statement (see [WRITE], page 360)

- 4. Any attempt to open a file that is already open will fail with a file status of 41 (see [File Status Codes], page 98).
- 5. Any open failure (including status 41) may be trapped using DECLARATIVES (see [DECLARATIVES], page 218) or an error procedure established using the CBL_ERROR_PROC built-in system subroutine (see [CBL_ERROR_PROC], page 501) built-in subroutine or even just checking the status field defined. It is up to the programmer to check for bad statuses and respond accordingly such as issue a CLOSE before dealing with the problem.
- 6. The INPUT, OUTPUT, I-O and EXTEND open modes inform GnuCOBOL of the manner in which you wish to use the file, as follows:

INPUT You may only read the existing contents of the file — only the CLOSE, READ, START and UNLOCK statements will be allowed. This enforcement takes place at execution time, not compilation time.

OUTPUT You may only write new content (which will completely replace any previous file contents) to the file — only the CLOSE, UNLOCK and WRITE statements will be allowed. This enforcement takes place at execution time, not compilation time

I-O You may perform any operation you wish against the file — all file I/O statements will be allowed.

You may only write new content (which will be appended after the previously existing file contents) to the file — only the CLOSE, UNLOCK and WRITE statements will be allowed. This enforcement takes place at execution time, not compilation time. You cannot extend an empty file; this will not generate a runtime error, but no output will appear in the file.

- 7. The SHARING clause informs the GnuCOBOL file runtime modules how you are willing to co-exist with any other GnuCOBOL programs that may attempt to open the same file after your program does. See [File Sharing], page 52, for an explanation of the SHARING clause.
- 8. The WITH LOCK option will be functional only if your GnuCOBOL build can support it. GnuCOBOL built for MinGW or native Windows will not, because the Unix fcntl primitive doesn't exist in those environments. GnuCOBOL built for Cygwin or Unix will.

#### 7.8.30. PERFORM

#### 7.8.30.1. Procedural PERFORM

#### **Procedural PERFORM Syntax** PERFORM procedure-name-1 [ THRU|THROUGH procedure-name-2 ] [ { [ WITH TEST { BEFORE } ] { VARYING-Clause } } ] ~~~~ { ~~~~~~ } { UNTIL conditional-expression-1 } } { { { AFTER { } { UNTIL EXIT|FOREVER } } { { literal-1 } TIMES { { identifier-1 } ~~~~~ }

This format of the PERFORM statement is used to transfer control to one or more procedures, which will return control back when complete. Execution of the procedure(s) can be done a single time, multiple times, repeatedly until a condition becomes TRUE or forever (with some way of breaking out of the control of the PERFORM or of halting program execution within the procedure(s)).

- 1. The reserved word WITH is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. The reserved words THRU and THROUGH are interchangeable.
- 3. The reserved word and phrase FOREVER and UNTIL EXIT are interchangeable.
- 4. Both procedure-name-1 and procedure-name-2 must be procedure division sections or paragraphs defined in the same program as the PERFORM statement. If procedure-name-2 is specified, it must follow procedure-name-1 in the program's source code.
- 5. The perform scope is defined as being the statements within procedure-name-1, the statements within procedure-name-2 and all statements in all procedures defined between them.
- 6. *literal-1* must be a numeric literal or a reference to a function that returns a numeric value. The value must be an integer greater than zero.
- 7. identifier-1 must be an elementary un-edited numeric data item with an integer value greater than zero.
- 8. Without the UNTIL, UNTIL EXIT, TIMES, VARYING-Clause (see [VARYING], page 314) or FOREVER clauses, the code within the perform scope will be executed once, after which control will return to the statement following the PERFORM.
- 9. The FOREVER option will repeatedly execute the code within the perform scope with no conditions defined for termination of the repetition it will be up to the programmer to include an EXIT SECTION statement (see [EXIT], page 282) or EXIT PARAGRAPH statement within the procedure(s) being performed that will break out of the loop.
- 10. The TIMES option will repeat the execution of the code within the perform scope a fixed number of times. When the PERFORM statement begins execution, an internal repeat counter (not accessible to the programmer) will be set to the value of *literal-1* or the value within *identifier-1*.

If the counter has a value greater than zero, the statement(s) within the PERFORM scope will be executed, after which the counter will be decremented by 1 with each repetition. Once that counter reaches zero, repetition will cease and control will fall into the next statement following the PERFORM.

If the *identifier-1* option was used, altering the value of that data item within the perform scope will *not* affect the repetition count.

- 11. The UNTIL conditional-expression-1 option will repeat the code within the perform scope until the specified conditional expression evaluates to a TRUE value.
- 12. The optional WITH TEST clause will control whether UNTIL testing occurs BEFORE the statements within the perform scope are executed on each iteration (creating the possibility if conditional-expression-1 is initially TRUE that the statements within the perform scope will never be executed) or AFTER (guaranteeing the statements within the perform scope will be executed at least once).

The default, if this clause is absent, is WITH TEST BEFORE.

This clause may not be coded when the TIMES clause is used.

13. The optional VARYING-Clause is a mechanism that creates an advanced loop-management mechanism complete with one or more numeric data items being automatically incremented (or decremented) on each loop iteration as well as the termination control of an UNTIL clause. See [VARYING], page 314, for the details.

#### 7.8.30.2. Inline PERFORM

# 

This format of the PERFORM statement is identical in operation to the procedural PERFORM, except for the fact that the statement(s) comprising the perform scope (*imperative-statement-1*) (see [Imperative Statement], page 632) are now specified in-line with the PERFORM code rather than in procedures located elsewhere within the program.

#### 7.8.30.3. VARYING

# VARYING Syntax

```
VARYING identifier-2 FROM { literal-2 } [ BY { literal-3 } ]

~~~~ { identifier-3 } ~~~ { identifier-4 }

[UNTIL conditional-expression-1]

~~~~~

[ AFTER identifier-5 FROM { literal-4 } [ BY { literal-5 } ]

~~~~~ { identifier-6 } ~~~ { identifier-7 }

[UNTIL conditional-expression-2]]...
```

The VARYING clause, available on both formats of the PERFORM statement, is a looping mechanism that allows for the specification of one or more numeric data items that will be initialized to a programmer-specified value and automatically incremented by another programmer-specified value after each loop iteration.

- 1. All identifiers used in a VARYING-Clause must be elementary, un-edited numeric data items. All literals must be numeric literals.
- 2. The following points describe the sequence of events that take place as a result of the VARYING portion of the clause:
  - A. When the PERFORM begins execution, the FROM value will be moved to identifier.
  - B. If the PERFORM specifies or implies WITH TEST BEFORE, conditional-expression-1 will be evaluated and processing of the PERFORM will halt if the expression evaluates to TRUE. If WITH TEST BEFORE was not specified or implied, or if the conditional expression evaluated to FALSE, processing proceeds with step C.
  - C. The statements within the perform scope will be executed. If a GO TO executed within the perform scope transfers control to a point outside the perform scope, processing of the PERFORM will halt.
  - D. When the statements within the perform scope terminate the loop iteration, by one of:
    - allowing the flow of execution to attempt to fall past the last statement in the perform scope
    - executing an EXIT PERFORM CYCLE statement (see [EXIT], page 282)
    - executing an EXIT PARAGRAPH statement or EXIT SECTION statement when there is only one paragraph (or section) in the perform scope (this option only applies to a procedural PERFORM)

If WITH TEST AFTER was specified, control will return back to the PERFORM, where conditional-expression-1 will be evaluated, and processing of the PERFORM will halt if the expression evaluates to TRUE. If WITH TEST AFTER was not specified, or if the conditional expression evaluated to FALSE, processing continues with the next step.

- E. The BY value, if any, will be added to *identifier-2*. If no BY is specified, it will be treated as if BY 1 had been specified.
- F. Return to step C.
- 3. Most VARYING-Clauses have no AFTER specified. Those that do, however, are establishing a loop-within-a-loop situation where the process described above in steps ('A') through ('F') will take place from the AFTER, and those six processing steps actually replace step C of the VARYING. This "nesting" process can continue indefinitely, with each additional AFTER.

An example should really help you see this at work. Observe the following code which defines a two-dimensional (3 row by 4 column) table and a pair of numeric data items to be used to subscript references to each element of the table:

```
 01
 PERFORM-DEMO.

 05
 PD-ROW
 OCCURS 3 TIMES.

 10
 PD-COL
 OCCURS 4 TIMES

 15
 PD
 PIC X(1).

 01
 PD-Col-No
 PIC 9 COMP.

 01
 PD-Row-No
 PIC 9 COMP.
```

Let's say the 3x4 "grid" defined by the above structure has these values:

```
A B C D
E F G H
I J K L
```

This code will display ABCDEFGHIJKL on the console output window:

```
PERFORM WITH TEST AFTER
```

```
VARYING PD-Row-No FROM 1 BY 1 UNTIL PD-Row-No = 3

AFTER PD-Col-No FROM 1 BY 1 UNTIL PD-Col-No = 4

DISPLAY PD (PD-Row-No, PD-Col-No) WITH NO ADVANCING
END-PERFORM
```

While this code will display AEIBFJCGKDHL on the console output window:

```
PERFORM WITH TEST AFTER
```

```
VARYING PD-Col-No FROM 1 BY 1 UNTIL PD-Col-No = 4
AFTER PD-Row-No FROM 1 BY 1 UNTIL PD-Row-No = 3
DISPLAY PD (PD-Row-No, PD-Col-No) WITH NO ADVANCING
END-PERFORM
```

While we're looking at sample code, this code displays ABCEFG:

```
PERFORM
```

```
VARYING PD-Row-No FROM 1 BY 1 UNTIL PD-Row-No = 3

AFTER PD-Col-No FROM 1 BY 1 UNTIL PD-Col-No = 4

DISPLAY PD (PD-Row-No, PD-Col-No) WITH NO ADVANCING
END-PERFORM
```

By removing the WITH TEST clause, the statement is now assuming WITH TEST BEFORE. Since testing now happens *before* the DISPLAY statement gets executed, when PD-Row-No is 3 and PD-Col-No is 4 the DISPLAY statement won't be executed.

Most COBOL programmers, when using WITH TEST BEFORE explicitly or implicitly have developed the habit of using '>' rather than '=' on UNTIL clauses. This would make the sample code:

```
PERFORM
```

```
VARYING PD-Row-No FROM 1 BY 1 UNTIL PD-Row-No > 3

AFTER PD-Col-No FROM 1 BY 1 UNTIL PD-Col-No > 4

DISPLAY PD (PD-Row-No, PD-Col-No) WITH NO ADVANCING
END-PERFORM
```

With this change, ABCDEFGHIJKL is once again displayed.

#### 7.8.31. READ

#### 7.8.31.1. Sequential READ

#### Sequential READ Syntax

```
READ file-name-1 [{ NEXT|PREVIOUS }] RECORD [INTO identifier-1]
 { ~~~~ }
 [{ IGNORING LOCK
 }]
 { ~~~~~~~
 { WITH [NO] LOCK }
 {
 { WITH KEPT LOCK
 {
 { WITH IGNORE LOCK }
          ~~~~~ ~~~
    {
    TIAW HTIW }
  [ AT END imperative-statement-1 ]
  [ NOT AT END imperative-statement-2 ]
[ END-READ ]
```

This form of the READ statement retrieves the next (or previous) record from a file.

- 1. The reserved words AT, RECORD and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The file-name-1 file must have been defined via an FD (see [File/Sort-Description], page 113), not an SD.
- 3. The file-name-1 file must currently be open for INPUT (see [File OPEN Modes], page 309) or I-0.
- 4. If file-name-1 is an ORGANIZATION RELATIVE (see [ORGANIZATION RELATIVE], page 103) or ORGANIZATION INDEXED (see [ORGANIZATION INDEXED], page 105) file with an ACCESS MODE RANDOM, this statement cannot be used.
- 5. If file-name-1 was specified as ACCESS MODE SEQUENTIAL, this is the only format of the READ statement that is available.
- 6. If file-name-1 is an ORGANIZATION RELATIVE (see [ORGANIZATION RELATIVE], page 103) or ORGANIZATION INDEXED (see [ORGANIZATION INDEXED], page 105) file with ACCESS MODE DYNAMIC, this statement as well as a random READ (see [Random READ], page 318) may be used.
- 7. The keywords NEXT and PREVIOUS specify what "direction of travel" the reading process will take through the file. If neither is specified, NEXT is assumed.
- 8. The PREVIOUS option is available only for ORGANIZATION INDEXED files.
- 9. When reading any sequential (any organization) or relative file, the "next" direction refers to the physical sequence of records in the file. When reading an indexed file, the "next"

- and "previous" directions refer to the sequence of primary or alternate record key values in the file's records, regardless of where the records physically occur within the file.
- 10. The minimal statement READ file-name-1 is perfectly legal according to both READ formats. For that reason, when ACCESS MODE DYNAMIC has been specified and you want to tell the GnuCOBOL compiler that this minimal statement should be treated as a sequential READ, you must add either NEXT or PREVIOUS to the statement (otherwise it will be treated as a random READ).
- 11. A successful sequential READ will retrieve the next available record from file-name-1, in either a "next" or "previous" direction from the most-recently-read record, depending upon the use of the NEXT or PREVIOUS option. The newly-retrieved record data will be saved into the 01-level record structure(s) that immediately follow the file's FD. If the optional INTO clause is present, a copy of the just-retrieved record will be automatically moved to identifier-1.
- 12. When an ORGANIZATION RELATIVE file has been successfully read, the file's RELATIVE KEY (see [ORGANIZATION RELATIVE], page 103) field will be automatically populated with the relative record number (ordinal occurrence number) of the record in the file.
- 13. The optional LOCK options may be used to manually control access to the retrieved record by other programs while this program is running. See [Record Locking], page 54, to review the various record locking behaviours.
- 14. The optional AT END clause, if coded, is used to detect and react to the failure of an attempt to retrieve another record from the file due to an end-of-file (i.e. no more records) condition.
- 15. The optional NOT AT END clause, if coded, will check for a file status value of 00. See [File Status Codes], page 98, for additional information.

#### 7.8.31.2. Random READ

#### Random READ Syntax

```
READ file-name-1 RECORD [ INTO identifier-1 ]
  [ { IGNORING LOCK
                       } ]
    { ~~~~~~
    { WITH [ NO ] LOCK }
    {
    { WITH KEPT LOCK
           ~~~~ ~~~~
 {
 { WITH IGNORE LOCK }
           ~~~~~ ~~~
    {
    TIAW HTIW }
  [ KEY IS identifier-2 ]
  [ INVALID KEY imperative-statement-1 ]
  [ NOT INVALID KEY imperative-statement-2 ]
[ END-READ ]
```

This form of the READ statement retrieves an arbitrary record from an ORGANIZATION RELATIVE (see [ORGANIZATION RELATIVE], page 103) or ORGANIZATION INDEXED (see [ORGANIZATION INDEXED], page 105) file.

- 1. The reserved words IS, KEY (on the INVALID and NOT INVALID clauses), RECORD and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The file-name-1 file must have been defined via an FD (see [File/Sort-Description], page 113), not an SD.
- 3. The file-name-1 file must currently be open for INPUT (see [File OPEN Modes], page 309) or I-0.
- 4. If the ACCESS MODE of file-name-1 is SEQUENTIAL, or the ORGANIZATION of the file is any form of sequential, this format of the READ statement cannot be used.
- 5. If the ACCESS MODE of file-name-1 is RANDOM, this is the only format of the READ statement that is available.
- 6. If file-name-1 is an ORGANIZATION RELATIVE (see [ORGANIZATION RELATIVE], page 103) or ORGANIZATION INDEXED (see [ORGANIZATION INDEXED], page 105) file with ACCESS MODE DYNAMIC, this statement as well as a sequential READ (see [Sequential READ], page 316) may be used.
- 7. The minimal statement READ file-name-1 is perfectly legal according to both READ formats. For that reason, when ACCESS MODE DYNAMIC has been specified and you want to tell the GnuCOBOL compiler that this minimal statement should be treated as a random READ, you must omit the NEXT or PREVIOUS available to the sequential format of the READ statement to ensure the statement will be treated as a random READ.

8. The optional KEY clause tells the compiler how a record is to be located in the file. If the KEY clause is absent, and the file is

#### ORGANIZATION RELATIVE

the contents of the field declared as the file's  ${\tt RELATIVE}$  KEY will be used to identify a record

#### ORGANIZATION INDEXED

the contents of the field declared as the file's RECORD KEY will be used to identify a record.

If the KEY clause is specified, and the file is

#### ORGANIZATION RELATIVE

the contents of *identifier-2* will be used as the relative record number of the record to be accessed. *identifier-2* need not be the RELATIVE KEY (see [ORGANIZATION RELATIVE], page 103) field of the file (although it could be if you wish).

#### ORGANIZATION INDEXED

identifier-2 must be the RECORD KEY (see [ORGANIZATION INDEXED], page 105) or one of the file's ALTERNATE RECORD KEY fields (if any). The current contents of that field will identify the record to be accessed. If an alternate record key is used, and that key allows duplicate values, the record accessed will be the *first* one having that key value.

- 9. Once read from the file, the newly-retrieved record data will be saved into the 01-level record structure(s) that immediately follow the file's FD. If the optional INTO clause is present, a copy of the just-retrieved record will be automatically moved to identifier-1.
- 10. When an ORGANIZATION RELATIVE file has been successfully read, the file's RELATIVE KEY (see [ORGANIZATION RELATIVE], page 103) field will be automatically populated with the relative record number (ordinal occurrence number) of the record in the file.
- 11. The optional LOCK options may be used to manually control access to the retrieved record by other programs while this program is running. See [Record Locking], page 54, to review the various record locking behaviours.
- 12. The optional INVALID KEY and NOT INVALID KEY clauses may be used to detect and react to the failure or success, respectively, by detecting non-zero (typically 23 = key not found = record not found) and 00 file status codes, respectively. See [File Status Codes], page 98, for additional information.

#### 7.8.32. READY TRACE

|         |       | READY TRACE Syntax |
|---------|-------|--------------------|
| READY T | TRACE |                    |
|         |       |                    |

The READY TRACE statement turns procedure or procedure-and-statement tracing on.

- 1. In order for this statement to be functional, tracing code must have been generated into the compiled program using either the —ftrace switch (procedures only) or —ftraceall switch (procedures and statements).
- 2. Tracing may be turned off at any point by executing the RESET TRACE statement (see [RESET TRACE], page 322).
- 3. The COB_SET_TRACE run-time environment variable (see [Run Time Environment Variables], page 584) provides another way to control tracing. If this environment variable is set to a value of 'Y' prior to the start of program execution, tracing starts at the point the program begins execution, as if READY TRACE were the first executed statement.

#### 7.8.33. RELEASE

```
RELEASE Syntax

RELEASE record-name-1 [ FROM { literal-1 } ]

~~~~ { identifier-1 }
```

The RELEASE statement adds a new record to a sort work file.

- 1. This statement is valid only within the INPUT PROCEDURE of a file-based SORT statement (see [File-Based SORT], page 339).
- 2. The specified record-name-1 must be a record defined to the sort description (SD (see [File/Sort-Description], page 113)) of the sort work file being processed by the current sort.
- 3. The optional FROM clause will cause literal-1 or identifier-1 to be automatically moved into record-name-1 prior to writing record-name-1's contents to the file-name-1. If this clause is not specified, it is the programmer's responsibility to populate record-name-1 with the desired data prior to executing the RELEASE.

#### 7.8.34. RESET TRACE

|       | RESET T | RACE Syntax |  |
|-------|---------|-------------|--|
| TRACE |         |             |  |
|       |         |             |  |

The RESET TRACE statement turns procedure or procedure-and-statement tracing off.

- 1. By default, procedure and procedure-and-statement tracing is off as programs begin execution. The READY TRACE statement (see [READY TRACE], page 320) can be used to turn tracing on.
- 2. In order for this statement to be functional, tracing code must have been generated into the compiled program using either the -ftrace switch (procedures only) or -ftraceall switch (procedures and statements).
- 3. The COB_SET_TRACE run-time environment variable (see [Run Time Environment Variables], page 584) provides another way to control tracing. If this environment variable is set to a value of 'Y' prior to the start of program execution, tracing started at the point the program begins execution, as if READY TRACE were the first executed statement. The RESET TRACE statement, if executed, will then turn off tracing.

#### 7.8.35. RETURN

#### **RETURN Syntax**

```
RETURN sort-file-name-1 RECORD

[INTO identifier-1]

AT END imperative-statement-1

[NOT AT END imperative-statement-2]

[END-RETURN]
```

The RETURN statement reads a record from a sort or merge work file.

- 1. The reserved words AT and RECORD are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The RETURN statement is valid only within the OUTPUT PROCEDURE of a file-based SORT (see [File-Based SORT], page 339) or a MERGE statement (see [MERGE], page 302) statement.
- 3. The sort-file-name-1 file must be a sort- or merge work file defined with a SD (see [File/Sort-Description], page 113), not an FD.
- 4. A successful RETURN will retrieve the next available record from *sort-file-name-1*. The newly-retrieved record data will be saved into the 01-level record structure(s) that immediately follow the file's SD. If the optional INTO clause is present, a copy of the just-retrieved record will be automatically moved to *identifier-1*.
- 5. The mandatory AT END clause is used to detect and react to the failure of an attempt to retrieve another record from the file due to an end-of-file (i.e. no more records) condition.
- 6. The optional NOT AT END clause, if coded, will check checking for a file status value of 00. See [File Status Codes], page 98, for additional information.

#### 7.8.36. REWRITE

#### **REWRITE Syntax**

```
REWRITE record-name-1

""""

[FROM { literal-1 }]

""" { identifier-1 }

[WITH [NO] LOCK]

""" """"

[INVALID KEY imperative-statement-1]

""" """"

[NOT INVALID KEY imperative-statement-2]

""" """""

[END-REWRITE]
```

The REWRITE statement replaces a logical record on a disk file.

- 1. The reserved words KEY and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The record-name-1 specified on the statement must be defined as an 01-level record subordinate to the File Description (FD (see [File/Sort-Description], page 113)) of a file that is currently open for I-O (see [File OPEN Modes], page 309).
- 3. The optional FROM clause will cause literal-1 or identifier-1 to be automatically moved into record-name-1 prior to writing record-name-1's contents to the file-name-1. If this clause is not specified, it is the programmer's responsibility to populate record-name-1 with the desired data prior to executing the REWRITE.
- 4. This statement may not be used with ORGANIZATION LINE SEQUENTIAL (see [ORGANIZATION LINE SEQUENTIAL], page 101) files.
- 5. Rewriting a record does not cause the contents of the file to be physically updated until the next block of the file is read, a COMMIT (see [COMMIT], page 259) or UNLOCK statement (see [UNLOCK], page 355) is issued or that file is closed.
- 6. If the file has ORGANIZATION SEQUENTIAL (see [ORGANIZATION SEQUENTIAL], page 100):
  - A. The record to be rewritten will be the one retrieved by the most-recently executed READ (see [READ], page 316) of the file.
  - B. If the FD of the file contains the RECORD CONTAINS or RECORD IS VARYING clause, and that clause allows the record size to vary, the size of record-name-1 cannot be altered.
- 7. If the file has ORGANIZATION RELATIVE (see [ORGANIZATION RELATIVE], page 103) or ORGANIZATION INDEXED (see [ORGANIZATION INDEXED], page 105):
  - A. If the file has ACCESS MODE SEQUENTIAL, the record to be rewritten will be the one retrieved by the most-recently executed READ of the file. If the file has ACCESS MODE RANDOM or ACCESS MODE DYNAMIC, no READ is required before a record may be rewritten—the RELATIVE KEY or RECORD KEY definition for the file, respectively, will specify the record to be updated.
  - B. If the FD of the file contains the RECORD CONTAINS or RECORD IS VARYING clause, and that clause allows the record size to vary, the size *can* be altered.

- 8. The optional LOCK options may be used to manually control access to the re-written record by other programs while this program is running. See [Record Locking], page 54, to review the various record locking behaviours.
- 9. The optional INVALID KEY and NOT INVALID KEY clauses may be used to detect and react to the failure or success, respectively, by detecting non-zero (typically 23 = key not found = record not found) and 00 file status codes, respectively. See [File Status Codes], page 98, for additional information.

## **7.8.37. ROLLBACK**

|          | ROLLBACK Syntax |  |
|----------|-----------------|--|
| ROLLBACK |                 |  |
|          |                 |  |

The ROLLBACK statement has the same effect as if an UNLOCK statement (see [UNLOCK], page 355) were executed against every open file in the program.

- 1. All locks currently being held for all open files will be released.
- 2. See [Record Locking], page 54, to review the various record locking behaviours.

#### 7.8.38. SEARCH

#### **SEARCH Syntax**

```
SEARCH table-name-1

[VARYING index-name-1]

[AT END imperative-statement-1]

[WHEN conditional-expression-1 imperative-statement-2 }...

[END-SEARCH]
```

The SEARCH statement is used to sequentially search a table, stopping either once a specific value is located within the table or when the table has been completely searched.

- 1. The reserved word AT is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. The searching process will be controlled through a Search Index a data item with a USAGE (see [USAGE], page 198) of INDEX. The search index is either the index-name-1 identifier specified on the VARYING clause or if no VARYING is specified the USAGE INDEX data item implicitly created by an INDEXED BY (see [OCCURS], page 172) clause in the table's definition.
- 3. At the time the SEARCH statement is executed, the current value of the search index data item will define the starting position in the table where the searching process will begin. Typically, one initializes that index to a value of 1 before starting the SEARCH via SET search-index TO 1.
- 4. Each of the *conditional-expression-ns* on the WHEN clause(s) should involve a data element within the table, subscripted using the search index.
- 5. The searching process is as follows:
  - A. Each conditional-expression-n will be evaluated, in turn, until either one evaluates to a value of TRUE or all have evaluated to FALSE.
  - B. The *imperative-statement-n* (see [Imperative Statement], page 632) specified on the WHEN clause whose *conditional-expression-n* evaluated to TRUE will be executed; after that, the search will be considered complete and control will fall into the first executable statement following the SEARCH.
  - C. If all conditional-expression-ns evaluated to FALSE:
    - The search index will be incremented by 1
    - If the search index now has a value greater than the number of entries in the table, the search is considered to have failed and the *imperative-statement-1* on the optional AT END clause, if any, will be executed. After that, control will fall into the first executable statement following the SEARCH.
    - If the search index now has a value less than or equal to the number of entries in the table, search processing returns back to step A.

#### **7.8.39. SEARCH ALL**

#### **SEARCH ALL Syntax**

```
SEARCH ALL table-name-1

[AT END imperative-statement-1]

WHEN conditional-expression-1 imperative-statement-2

END-SEARCH]
```

The SEARCH ALL statement performs a binary, or half-interval, search against a sorted table. This is generally *significantly* faster than performing a sequential SEARCH of a table, especially

1. The reserved word AT is optional and may be omitted. The presence or absence of this word has no effect upon the program.

2. To be eligible for searching via SEARCH ALL:

if the table contains a large number of entries.

- A. The OCCURS clause of table-name-1 must contain the following elements:
  - An INDEXED BY entry to define an implicit search index data item with a USAGE (see [USAGE], page 198) of INDEX.
  - An ASCENDING KEY or DESCENDING KEY clause to specify the field within the table by which all entries in the table are sorted.
- B. Just because the table has one or more KEY clauses doesn't mean the data is actually in that sequence in the table the actual sequence of the data must agree with the KEY clause(s)! A table-based SORT (see [Table SORT], page 342) can prove very useful in this regard.
- C. No two records in the table may have the same KEY field values. If the table has multiple KEY definitions, then no two records in the table may have the same *combination* of KEY field values.
- 3. If rule A is violated, the compiler will reject the SEARCH ALL. If rules B and/or C are violated, there will be no message issued by the compiler, but the run-time results of a SEARCH ALL against the table will probably be incorrect.
- 4. The *conditional-expression-1* should involve the KEY field(s), using the search index (the table's INDEXED BY index name) as a subscript.
- 5. The function of the single, mandatory, WHEN clause is to compare the key field(s) of the table, as indexed by the search index data item, against whatever literal and/or identifier values you are comparing the key field(s) to in the conditional-expression-1 in order to locate the desired entry in the table. The search index will be automatically varied in a manner designed to require the minimum number of tests.
- 6. The internal processing of the SEARCH ALL statement begins by setting internal "first" and "last" pointers to the 1st and last entry locations of the table. Processing then proceeds as follows:
  - A. The entry half-way between "first" and "last" is identified. We'll call this the "current" entry, and will set its table entry location into index-name-1.

- B. The *conditional-expression-1* is evaluated. This comparison of the key(s) against the target literal/identifier values will have one of three possible outcomes:
  - If the key(s) and value(s) match, *imperative-statement-2* (see [Imperative Statement], page 632) is executed, after which control falls through into the next statement following the SEARCH ALL.
  - If the key(s) are LESS THAN the value(s), then the table entry being searched for can only occur in the "current" to "last" range of the table, so a new "first" pointer value is set (it will be set to the "current" pointer).
  - If the key(s) are GREATER THAN the value(s), then the table entry being searched for can only occur in the "first" to "current" range of the table, so a new "last" pointer value is set (it will be set to the "current" pointer).
- C. If the new "first" and "last" pointers are different than the old "first" and "last" pointers, there's more left to be searched, so return to step A and continue.
- D. If the new "first" and "last" pointers are the same as the old "first" and "last" pointers, the table has been exhausted and the entry being searched for cannot be found; imperative-statement-1 is executed, after which control falls through into the next statement following the SEARCH ALL. If there is no AT END clause coded, control simply falls into the next statement following the SEARCH ALL.
- 7. The net effect of the above algorithm is that only a fraction of the number of elements in the table need ever be tested in order to decide whether or not a particular entry exists. This is because the half the remaining entries in the table are discarded each time an entry is checked.
- 8. Computer scientists will compare the two techniques implemented by the SEARCH and SEARCH ALL statements as follows:
- 9. When searching a table with N entries, a sequential search will need an average of N/2 tests and a worst case of N tests in order to find an entry and N tests to identify that an entry doesn't exist.
- 10. When searching a table with N entries, a binary search will need a worst-case of  $\log 2(N)$  tests in order to find an entry and  $\log 2(N)$  tests to identify that an entry doesn't exist (N = the number of entries in the table), where  $\log 2$  is the base-2 logarithm function.

Here's a more practical view of the difference. Let's say that a table has 1,000 entries in it. With a sequential search, on average, you'll have to check 500 of them to find an entry and you'll have to look at all 1,000 of them to find that an entry doesn't exist.

With a binary search, express the number of entries as a binary number (1,000 = 1111101000), count the number of digits in the result (which is, essentially, what a logarithm is, when rounded up to the next integer — the number of digits a decimal number would have if expressed in the logarithm's number base). In this case, we end up with 10 - that is the worst-case number of tests required to find an entry or to identify that it doesn't exist. That's quite an improvement!

#### 7.8.40. SET

#### 7.8.40.1. SET ENVIRONMENT

```
SET ENVIRONMENT Syntax

SET ENVIRONMENT { literal-1 } TO { literal-2 }
~~~~~~~~~~~~~~~~ { identifier-1 } ~~~ { identifier-2 }
```

The SET ENVIRONMENT statement provides a straight-forward means of setting environment values from within a program.

- 1. The value of literal-1 or identifier-1 specifies the name of the environment variable to set.
- 2. The value of *literal-2* or *identifier-2* specifies the value to be assigned to the environment variable.
- 3. Environment variables created or changed from within GnuCOBOL programs will be available to any sub-shell processes spawned by that program (i.e. CALL "SYSTEM") but will not be known to the shell or console window that started the GnuCOBOL program.

This is a much simpler and more readable means of setting environment variables than by using the DISPLAY UPON ENVIRONMENT-NAME statement (see [DISPLAY UPON ENVIRONMENT-NAME], page 265). For example, these two code sequences produce identical results:

```
DISPLAY "VARNAME" UPON ENVIRONMENT-NAME DISPLAY "VALUE" UPON ENVIRONMENT-VALUE
```

SET ENVIRONMENT "VARNAME" TO "VALUE"

#### 7.8.40.2. SET Program-Pointer

```
SET Program-Pointer Syntax

SET program-pointer-1 TO ENTRY { literal-1 }

~~~~~~~~~~~ { identifier-1 }
```

The SET *Program-Pointer* statement allows you to retrieve the address of a procedure division code module — specifically the PROGRAM-ID, FUNCTION-ID or an entry-point established via the ENTRY statement (see [ENTRY], page 275).

- 1. The USAGE (see [USAGE], page 198) of program-pointer-1 must be PROGRAM-POINTER.
- 2. The *literal-1* or *identifier-1* value specified must name a primary entry-point name (PROGRAM-ID of a subroutine or FUNCTION-ID of a user-defined function) or an alternate entry-point defined via an ENTRY statement within a subprogram.
- 3. Once the address of a procedure division code area has been acquired in this way, the address could be passed to a subroutine (usually written in C) for whatever use it needs it for. For examples of PROGRAM-POINTERs at work, see the discussions of the CBL_ERROR_PROC built-in system subroutine (see [CBL_ERROR_PROC], page 501) and CBL_EXIT_PROC built-in system subroutine (see [CBL_EXIT_PROC], page 503).

#### **7.8.40.3. SET ADDRESS**

The SET ADDRESS statement can be used to work with the addresses of data items rather than their contents.

- 1. When the ADDRESS OF clause is used *before* the TO you will be using this statement to alter the address of a linkage section or BASED (see [BASED], page 145) data item. Without that clause you will be assigning an address to one or more data items whose USAGE (see [USAGE], page 198) is POINTER.
- 2. When the ADDRESS OF clause is used after the TO, this statement will be identifying the address of identifier-2 as the address to be assigned to identifier-1 or stored in pointer-name-1.
- 3. If the ADDRESS OF clause is absent after the TO, the contents of *pointer-name-2* will serve as the address to be assigned.

## 7.8.40.4. SET Index

```
SET Index Syntax

SET index-name-1 TO { literal-1 }
~~~ { identifier-2 }
```

This statement assigns a value to a  ${\tt USAGE}$  INDEX data item.

1. Either the USAGE (see [USAGE], page 198) of index-name-1 should be INDEX, or index-name-1 must be identified in a table INDEXED BY clause.

# 7.8.40.5. SET UP/DOWN

Use this statement to increment or decrement the value of an index or pointer by a specified amount.

- 1. The USAGE (see [USAGE], page 198) of identifier-1 must be INDEX, POINTER or PROGRAM-POINTER.
- 2. The typical usage when *identifier-1* is a USAGE INDEX data item is to increment its value UP or DOWN by 1, since an index is usually being used to sequentially walk through the elements of a table.

#### 7.8.40.6. SET Condition Name

The SET Condition Name statement provides one method of specifying the TRUE / FALSE value of a level-88 condition name.

- 1. By setting the specified *condition-name-1*(s) to a TRUE or FALSE value, you will actually be assigning a value to the parent data item(s) to which the condition name data item(s) is(are) subordinate to.
- 2. When specifying TRUE, the value assigned to each parent data item will be the first value specified on the condition name's VALUE clause.
- 3. When specifying FALSE, the value assigned to each parent data item will be the value specified for the FALSE clause of the condition name's definition; if any *condition-name-1* occurrence lacks a FALSE clause, the SET statement will be rejected by the compiler.


## 7.8.40.7. SET Switch

# SET Switch Syntax

This form of the SET statement is used to turn switches on or off.

- 1. Switches are defined using the SPECIAL-NAMES (see [SPECIAL-NAMES], page 84) paragraph.
- 2. Switches may be tested via the IF statement (see [IF], page 291) and a Switch-Status Condition. See [Switch-Status Conditions], page 45, for more information.

#### **7.8.40.8. SET ATTRIBUTE**



The SET ATTRIBUTE statement may be used to modify one or more attributes of a screen section data item at run-time.

- 1. When making an attribute change to *identifier-1*, the change will not become visible on the screen until the screen section data item containing *identifier-1* is next accepted (if *identifier-1* is an input field) or is next displayed (if *identifier-1* is not an input field).
- 2. The attributes shown in the syntax diagram are the only ones that may be altered by this statement. See [Data Description Clauses], page 140, for information on their usage.

## 7.8.40.9. SET LAST EXCEPTION

# SET LAST EXCEPTION TO { OFF }

The SET LAST EXCEPTION statement will set the last program exception status to indicate no exception.

- 1. The predefined object reference EXCEPTION-OBJECT is set to null, and the last exception status is set to indicate no exception.
- 2. This action resets the global exception object completely (FUNCTION EXCEPTION-{FILE, LOCATION, STATEMENT, STATUS}), and will not show anything afterwards), no matter what the last exception was (such as a divide by zero). Use with care.

#### 7.8.41. SORT

#### 7.8.41.1. File-Based SORT

# File-Based SORT Syntax

```
SORT sort-file-1
   { ON { ASCENDING } KEY identifier-1... }...
       { ~~~~~ }
        { DESCENDING }
   [ WITH DUPLICATES IN ORDER ]
   [ COLLATING SEQUENCE IS alphabet-name-1 ]
   { INPUT PROCEDURE IS procedure-name-1
                                                }
   {
           [ THRU|THROUGH procedure-name-2 ]
                                                }
            ~~~~ ~~~~~~
 }
 {
 { USING file-name-1 ...
 }
 { OUTPUT PROCEDURE IS procedure-name-3
 [THRU|THROUGH procedure-name-4]
 {
 }
 {
 }
 }
 { GIVING file-name-2 ...
     ~~~~~
```

The DUPLICATES clause is syntactically recognized but is otherwise non-functional.

This format of the SORT statement is designed to sort large volumes of data according to one or more key fields.

- 1. The reserved words IN, IS, KEY, ON, ORDER, SEQUENCE and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved words THRU and THROUGH are interchangeable.
- 3. GnuCOBOL always behaves as if the WITH DUPLICATES IN ORDER clause is specified, even if it isn't.

While any COBOL implementation's sort or merge facilities guarantee that records with duplicate key values will be in proper sequence with regard to other records with different key values, they generally make no promises as to the resulting relative sequence of records having duplicate key values with one another.

Some COBOL implementations provide this optional clause to force their sort and merge facilities to retain duplicate key-value records in their original input sequence, relative to one another.

4. The sort-file-1 named on the SORT statement must be defined using a sort description (SD

(see [File/Sort-Description], page 113)). This file is referred to in the remainder of this discussion as the *sort work file*.

- 5. If specified, file-name-1 and file-name-2 must reference ORGANIZATION LINE SEQUENTIAL (see [ORGANIZATION LINE SEQUENTIAL], page 101) or ORGANIZATION SEQUENTIAL (see [ORGANIZATION SEQUENTIAL], page 100) files. These files must be defined using a file description (FD (see [File/Sort-Description], page 113)). The same file(s) may be used for file-name-1 and file-name-2.
- 6. The identifier-1 . . . field(s) must be defined as field(s) within a record of sort-file-1.
- 7. A sort work file is never opened or closed.
- 8. The sorting process works in three stages the Input Stage, the Sort Stage and the Output Stage.
- 9. The following points pertain to the Input Stage:
  - A. The data to be sorted is loaded into the sort work file either by copying the entire contents of the file(s) named on the USING clause (done automatically by the sort) or by utilizing an input procedure.
  - B. When USING is specified, none of the *file-name-1* files may be open at the time the SORT statement is executed.
  - C. When an input procedure is used, the procedure(s) specified on the INPUT PROCEDURE clause will be invoked as if by a procedural PERFORM statement (see [Procedural PERFORM], page 311) with no VARYING, TIMES or UNTIL options specified. Records will be loaded into the sort work file one at a time within the input procedure using the RELEASE statement (see [RELEASE], page 321). This, by the way, is how you could sort the contents of relative or indexed files.

A GO TO statement (see [GO TO], page 288) that transfers control out of the input procedure will terminate the SORT statement but allows the program to continue executing from the point where the GO TO statement transferred control to. Once an input procedure has been "aborted" using a GO TO it cannot be resumed, and the contents of the sort work file are lost. You may, however, re-execute the SORT statement itself.¹

An input procedure should be terminated in the same way a procedural PERFORM statement would be.

Neither a another file-based SORT statement nor a MERGE statement may be executed within the input procedure unless those statements utilize a different sort or merge work file.

- D. Once the input procedure terminates, the input phase is complete.
- E. As data is loaded into the sort work file, it is actually being buffered in dynamically-allocated memory. Only if the amount of data to be sorted exceeds the amount of available sort memory (128 MB) will actual disk files be allocated and utilized. There is a COB_SORT_MEMORY run-time environment variable (see [Run Time Environment Variables], page 584) that you may use to allocate more or less memory to the sorting process.
- 10. The following points pertain to the Sort Stage:
  - A. The sort will take place by arranging the data records in the sequence defined by the KEY specification(s) on the SORT statement according to the COLLATING SEQUENCE specified on the SORT (if any) or if none was defined the PROGRAM COLLATING SEQUENCE (see [OBJECT-COMPUTER], page 82). Keys may be any supported data type and USAGE (see [USAGE], page 198) except for level-78 or level-88 data items.

Using a GO TO statement to prematurely terminate a sort, or re-starting a previously-cancelled sort is not considered good programming style and should be avoided.

B. For example, let's assume we're sorting a series of financial transactions. The SORT statement might look like this:

SORT Sort-File

ASCENDING KEY Transaction-Date
ASCENDING KEY Account-Number
DESCENDING KEY Transaction-Amount

The effect of this statement will be to sort all transactions into ascending order of the date the transaction took place (oldest first, newest last). Unless the business running this program is going out of business, there are most-likely many transactions for any given date. Therefore, within each grouping of transactions all with the same date, transactions will be sub-sorted into ascending sequence of the account number the transactions apply to. Since it's quite possible there might be multiple transactions for an account on any given date, a third level sub-sort will arrange all transactions for the same account on the same date into descending sequence of the actual amount of the transaction (largest first, smallest last). If two or more transactions of \$100.00 were recorded for account #12345 on the 31st of August 2009, those transactions will be retained in the order in which they were loaded into the sort work file.

- C. Should disk work files be necessary due to the amount of data being sorted, they will be automatically allocated to disk in a folder defined by the TMPDIR run-time environment variable, TMP run-time environment variable or TEMP run-time environment variable run-time environment variables (see [Run Time Environment Variables], page 584) (checked for existence in that sequence). These disk files will be automatically purged upon SORT termination or program execution termination (normal or otherwise).
- 11. The following points pertain to the Output Stage:
  - A. Once the sort stage is complete, a copy of the sorted data will be written to each file-name-2 if the GIVING clause was specified. None of the file-name-2 files can be open at the time the sort is executed.
  - B. When an output procedure is used, the procedure(s) specified on the OUTPUT PROCEDURE clause will be invoked as if by a procedural PERFORM statement (see [Procedural PERFORM], page 311) with no VARYING, TIMES or UNTIL options specified. Records will be retrieved from the sort work file one at a time within the output procedure using the RETURN statement (see [RETURN], page 323).

A GO TO statement (see [GO TO], page 288) that transfers control out of the output procedure will terminate the SORT statement but allows the program to continue executing from the point where the GO TO statement transferred control to. Once an output procedure has been "aborted" using a GO TO it cannot be resumed, and the contents of the sort work file are lost. You may, however, re-execute the SORT statement itself. USING A GO TO statement²

An output procedure should be terminated in the same way a procedural PERFORM statement would be.

Neither a another file-based SORT statement nor a MERGE statement may be executed within the output procedure unless those statements utilize a different sort or merge work file.

C. Once the output procedure terminates, the sort is complete.

 $^{^2}$  To prematurely terminate a sort, or re-starting a previously-cancelled sort is not considered good programming style and should be avoided.

#### 7.8.41.2. Table SORT

#### Table SORT Syntax

The DUPLICATES clause is syntactically recognized but is otherwise non-functional.

This format of the SORT statement sorts relatively small quantities of data — namely data contained in a data division table — according to one or more key fields.

- 1. The reserved words IN, IS, KEY, ON, ORDER, SEQUENCE and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. GnuCOBOL always behaves as if the WITH DUPLICATES IN ORDER clause is specified, even if it isn't.

While any COBOL implementation's sort or merge facilities guarantee that records with duplicate key values will be in proper sequence with regard to other records with different key values, they generally make no promises as to the resulting relative sequence of records having duplicate key values with one another.

Some COBOL implementations provide this optional clause to force their sort and merge facilities to retain duplicate key-value records in their original input sequence, relative to one another.

- 3. The *table-name-1* data item must be a table defined in any data division section *except* the report or screen sections.
- 4. The data within table-name-1 will be sorted in-place (i.e. no sort file is required).
- 5. The sort will take place by rearranging the data in table-name-1 into the sequence defined by the KEY specification(s) on the SORT statement, according to the COLLATING SEQUENCE specified on the SORT (if any) or if none was defined the PROGRAM COLLATING SEQUENCE (see [OBJECT-COMPUTER], page 82). Keys may be any supported data type and USAGE (see [USAGE], page 198) except for level-78 or level-88 data items.
- 6. If you are sorting table-name-1 for the purpose of preparing the table for use with a SEARCH ALL statement (see [SEARCH ALL], page 328), care must be taken that the KEY specifications on the SORT agree with those in the table's definition.
- 7. Although the specification of one or more KEY clauses is optional, currently, a table sort with no KEY specification(s) made on the SORT statement is unsupported by GnuCOBOL and will be rejected by the compiler.

#### 7.8.42. START

#### START Syntax START file-name-1 [ { FIRST } ] { ~~~~ } { LAST } { ~~~~ } { KEY { IS EQUAL TO | IS = | EQUALS } identifier-1 } } { IS GREATER THAN | IS > } { } { IS GREATER THAN OR EQUAL TO | IS >= } ~~~~~ } { IS NOT LESS THAN } { IS LESS THAN | IS < } } } { IS LESS THAN OR EQUAL TO | IS <= ~~~~ } } { IS NOT GREATER THAN [ WITH {SIZE} arithmetic-expression ] {LENGTH} arithmetic-expression ] [ INVALID KEY imperative-statement-1 ] [ NOT INVALID KEY imperative-statement-2 ]

The START statement defines the logical starting point within a relative or indexed file for subsequent sequential read operations. It positions an internal logical record pointer to a particular record in the file, but does not actually transfer any of that record's data into the record buffer.

- 1. The reserved words IS, THAN and TO are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. To use this statement, file-name-1 must be an ORGANIZATION RELATIVE (see [ORGANIZATION RELATIVE], page 103) or ORGANIZATION INDEXED (see [ORGANIZATION INDEXED], page 105) file that must have been defined with an ACCESS MODE DYNAMIC or ACCESS MODE SEQUENTIAL in its SELECT statement (see [SELECT], page 95).
- 3. At the time this statement is executed, *file-name-1* must be open in either INPUT or I-O (see [File OPEN Modes], page 309) mode.

[ END-START ]

- 4. If file-name-1 is a relative file, identifier-1 must be the defined RELATIVE KEY of the file.
- 5. If file-name-1 is an indexed file, identifier-1 must be the defined RECORD KEY of the file or any of the ALTERNATE RECORD KEY fields for the file.
- 6. If no FIRST, LAST or KEY clause is specified, KEY IS EQUAL TO xxx will be assumed, where xxx is the defined RELATIVE KEY of (if file-name-1 is a relative file) or the defined RECORD KEY (if file-name-1 is an indexed file).
- 7. After successful execution of a START statement, the internal logical record pointer into the file-name-1 data will be positioned to the record which satisfied the actual or implied FIRST, LAST or KEY clause specification, as follows:

FIRST the logical record pointer will point to the first record in the file.

LAST the logical record pointer will point to the last record in the file.

KEY (specified or implied), and the relation used is. Warning: Later versions of the compiler may well not use implied, so always specify it and it makes the code easier to read any way.

SIZE WITH SIZE or LENGTH arithmetic-expression specifies the number of characters in the key to be used in the positioning process.

LENGTH WITH LENGTH or SIZE arithmetic-expression specifies the number of characters in the key to be used in the positioning process.

SIZE and LENGTH are interchangeable and mean exactly the same.

#### EQUAL TO, GREATER THAN or GREATER THAN OR EQUAL TO (or equivalent)

the logical record pointer will be specified to the *first* record satisfying the relation condition; to identify this record. The file's contents are searched in a first-to-last (in sequence of the key implied by the KEY clause), provided the relation is

LESS THAN, LESS THAN OR EQUAL TO or NOT GREATER THAN (or equivalent)

the logical record pointer will be specified to the *last* record satisfying the relation condition; to identify this record. The file's contents are searched in a last-to-first (in sequence of the key implied by the KEY clause)

The next sequential READ statement will read the record that is pointed to by the logical record pointer.

8. The optional INVALID KEY and NOT INVALID KEY clauses may be used to detect and react to the failure or success, respectively, by detecting non-zero (typically 23 = key not found = record not found) and 00 file status codes, respectively. See [File Status Codes], page 98, for additional information.

#### 7.8.43. STOP

```
STOP Syntax
                                                    } ] }
STOP { RUN [ { RETURNING|GIVING { literal-1
                { ~~~
           {
                                                        }
    {
           {
                                                        }
    {
           { WITH { ERROR } STATUS [ { literal-2
                                                } ] }
                 { ~~~~ }
    {
           {
                                   { identifier-2 }
                                                        }
    {
                                                    }
           {
                 { NORMAL }
                                                        }
                                                        }
    {
                                                        }
    { literal-3
```

The STOP statement suspends program execution. Some options will allow program execution to resume while others return control to the operating system.

- 1. The reserved words STATUS and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved words RETURNING and GIVING are interchangeable.
- 3. The RUN clause halts the program without displaying any special message to that effect.
- 4. The *literal-3* clause displays the specified text on the SYSOUT/STDOUT device, waits for the user to press the Enter key and then once the key has been pressed allows the program to continue execution.
- 5. The optional RETURNING clause provides the opportunity to return a numeric value to the operating system (an exit status). The manner in which the exit status may be interrogated by the operating system varies, but Windows can use %ERRORLEVEL% to query the exit status while Unix shells such as sh, bash and ksh can query the exit status as \$?. Other Unix shells may have different ways to access return code values.
- 6. The STATUS clause provides another means of returning an exit status. Using the STATUS clause is functionally equivalent to using the RETURNING clause.
- 7. Using the STATUS clause without a *literal-2* or *identifier-2* will return an exit status of 0 if the NORMAL keyword is used or a 1 if ERROR was specified.
- 8. Your program will always return an exit status, even if no RETURNING or STATUS clause is specified. In the absence of the use of these clauses, the value in the RETURN-CODE special register (see [Special Registers], page 227) at the time the STOP statement is executed will be used as the exit status.
- 9. Any programmer-defined exit procedure (established via the CBL_EXIT_PROC built-in system subroutine (see [CBL_EXIT_PROC], page 503)) will be executed by STOP RUN, but not by STOP literal-3.
- 10. Valid return code values can be in the range -2147483648 to +2147483647.
- 11. The three code snippets below are all equivalent. They show different ways in which a GnuCOBOL program may be coded to pass an exit status value of 16 back to the operating system and then halt.

```
1.

STOP RUN RETURNING 16
2.

MOVE 16 TO RETURN-CODE STOP RUN
```

3. STOP RUN WITH ERROR STATUS 16

### 7.8.44. STRING

### STRING Syntax

The STRING statement is used to concatenate all or a part of one or more strings together, forming a new string.

- 1. The reserved words BY, ON and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. All literals and identifiers (except for *identifier-4*) must be explicitly or implicitly defined with a USAGE (see [USAGE], page 198) of DISPLAY. Any of the identifiers may be group items.
- 3. The POINTER data item identifier-4 must be a non-edited elementary integer numeric data item with a value greater than zero.
- 4. Each literal-1 / identifier-1 will be referred to as a source item. The receiving data item is identifier-3.
- 5. The STRING statement's processing is based upon a current character pointer. The initial value of the current character pointer will be the value of identifier-4 at the time the STRING statement began execution. If no POINTER clause is coded, a value of 1 (meaning "the 1st character position") will be assumed for the current character pointer's initial value.
- 6. For each source item, the contents of the sending item will be copied character-by-character into *identifier-3* at the character position specified by the current character pointer. After each character is copied, the current character pointer will be incremented by 1 so that it points to the position within *identifier-3* where the *next* character should be copied.
- 7. The DELIMITED BY clause specifies how much of each source item will be copied into identifier-3. DELIMITED BY SIZE (the default if no DELIMITED BY clause is specified) causes the entire contents of the source item to be copied into identifier-3.
- 8. Using DELIMITED BY *literal-2* or DELIMITED BY *identifier-2* causes only the contents of the source item up to but not including the character sequence specified by the literal or identifier to be copied.

- 9. STRING processing will cease when one of the following occurs:
  - A. The initial value of the current character pointer is less than 1 or greater than the number of characters in *identifier-3*, or...
  - B. The value of the current character pointer exceeds the size of *identifier-3* at the point the STRING statement wants to copy a character into *identifier-3*, or...
  - C. All sending items have been fully processed
- 10. If event A occurs, identifier-3 will remain unchanged.
- 11. The occurrence of either event A or B triggers what is referred to as an overflow condition.
- 12. The *identifier-3*) is neither automatically initialized (to spaces or any other value) at the start of a STRING statement nor will it be space-filled should the total number of sending item characters copied into it be less than its size. You may explicitly initialize *identifier-3* yourself via the INITIALIZE (see [INITIALIZE], page 292) or MOVE (see [MOVE], page 305) statements before executing the STRING if you wish.
- 13. The optional ON OVERFLOW and NOT ON OVERFLOW clauses may be used to detect and react to the occurrence or not, respectively, of an overflow condition. See [ON OVERFLOW + NOT ON OVERFLOW], page 223, for additional information.

### **7.8.45. SUBTRACT**

### 7.8.45.1. SUBTRACT FROM

```
SUBTRACT FROM Syntax
 SUBTRACT { literal-1
                    }... FROM { identifier-2
 ~~~~~~ { identifier-1 }
 { NEAREST-AWAY-FROM-ZERO }
 { ~~~~~~ }
 { NEAREST-EVEN
 }
 { ~~~~~~~
 { NEAREST-TOWARD-ZERO
 {
 { PROHIBITED
 }
                         ~~~~~~~~
                       {
                                            }
                       { TOWARD-GREATER
                                            }
                                           }
                                           }
                       { TOWARD-LESSER
                         ~~~~~~~~~~~
 }
 { TRUNCATION
 [ON SIZE ERROR imperative-statement-1]
 [NOT ON SIZE ERROR imperative-statement-2]
[END-SUBTRACT]
```

This format of the SUBTRACT statement generates the arithmetic sum of all arguments that appear before the FROM (identifier-1 or literal-1) and subtracts that sum from each identifier-2.

- 1. The reserved words IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. Both identifier-1 and identifier-2 must be numeric unedited data items.
- 3. literal-1 must be a numeric literal.
- 4. The optional ROUNDED (see [ROUNDED], page 224) clause available to each identifier-2 will control how non-integer results will be saved.
- 5. The optional ON SIZE ERROR and NOT ON SIZE ERROR clauses may be used to detect and react to the failure or success, respectively, of an attempt to perform a calculation. In this case, failure is defined as being an *identifier-2* with an insufficient number of digit positions available to the left of any implied decimal point. See [ON SIZE ERROR + NOT ON SIZE ERROR], page 223, for additional information.

### 7.8.45.2. SUBTRACT GIVING

```
SUBTRACT GIVING Syntax
 }... FROM identifier-2
 SUBTRACT { literal-1
 ~~~~~~ { identifier-1 }
     GIVING { identifier-3
        [ ROUNDED [ MODE IS { AWAY-FROM-ZERO
                                               } ] ] }...
                          { ~~~~~~~~
                  ~~~~
          ~~~~~
                           { NEAREST-AWAY-FROM-ZERO }
                                                  }
                           { NEAREST-EVEN
                                                  }
                            ~~~~~~~~~~~
 {
 }
 { NEAREST-TOWARD-ZERO
 }
 {
 }
 }
 { PROHIBITED
                             ~~~~~~~~~
                           {
                                                  }
                           { TOWARD-GREATER
                                                  }
                            ~~~~~~~~~~~~~~
 }
 { TOWARD-LESSER
 }
 { ~~~~~~~
 }
 { TRUNCATION
 [ON SIZE ERROR imperative-statement-1]
 [NOT ON SIZE ERROR imperative-statement-2]
[END-SUBTRACT]
```

The SUBTRACT GIVING statement generates the arithmetic sum of all arguments that appear before the FROM (*identifier-1* or *literal-1*), subtracts that sum from the contents of *identifier-2* and then replaces the contents of the identifiers listed after the GIVING (*identifier-3*) with that result.

- 1. The reserved words IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. Both identifier-1 and identifier-2 must be numeric unedited data items.
- 3. literal-1 must be a numeric literal.
- 4. identifier-3 must be a numeric (edited or unedited) data item.
- 5. The optional ROUNDED (see [ROUNDED], page 224) clause available to each *identifier-2* will control how non-integer results will be saved.
- 6. The optional ON SIZE ERROR and NOT ON SIZE ERROR clauses may be used to detect and react to the failure or success, respectively, of an attempt to perform a calculation. In this case, failure is defined as being an *identifier-2* with an insufficient number of digit positions available to the left of any implied decimal point. See [ON SIZE ERROR + NOT ON SIZE ERROR], page 223, for additional information.

### 7.8.45.3. SUBTRACT CORRESPONDING

### SUBTRACT CORRESPONDING Syntax SUBTRACT CORRESPONDING identifier-1 FROM identifier-2 [ ROUNDED [ MODE IS { AWAY-FROM-ZERO } ] ] { ~~~~~~~~ } { NEAREST-AWAY-FROM-ZERO } { ~~~~~~ } { NEAREST-EVEN { NEAREST-TOWARD-ZERO { PROHIBITED } { ~~~~~~ } } { TOWARD-GREATER { ~~~~~~~~ { TOWARD-LESSER } ~~~~~~~~~~~~ } { TRUNCATION [ ON SIZE ERROR imperative-statement-1 ] [ NOT ON SIZE ERROR imperative-statement-2 ] [ END-SUBTRACT ]

The SUBTRACT CORRESPONDING statement generates code equivalent to individual SUBTRACT FROM statements for corresponding matches of data items found subordinate to the two identifiers.

- 1. The reserved words IS and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. Both identifier-1 and identifier-2 must be group items.
- 3. See [CORRESPONDING], page 221, for information on how corresponding matches will be found between *identifier-1* and *identifier-2*.
- 4. The optional ROUNDED (see [ROUNDED], page 224) clause available to each identifier-2 will control how non-integer results will be saved.
- 5. The optional ON SIZE ERROR and NOT ON SIZE ERROR clauses may be used to detect and react to the failure or success, respectively, of an attempt to perform a calculation. In this case, failure is defined as being an *identifier-2* with an insufficient number of digit positions available to the left of any implied decimal point. See [ON SIZE ERROR + NOT ON SIZE ERROR], page 223, for additional information.

### **7.8.46. SUPPRESS**

| SUPPRESS Syntax   |  |  |
|-------------------|--|--|
| SUPPRESS PRINTING |  |  |
|                   |  |  |

The SUPPRESS statement causes the presentation of a report group to be suppressed.

- 1. The reserved word PRINTING is optional and may be omitted. The presence or absence of this word has no effect upon the program.
- 2. This statement may only appear within a USE BEFORE REPORTING procedure (in DECLARATIVES (see [DECLARATIVES], page 218)).
- 3. SUPPRESS only prevents the presentation of the report group within whose USE BEFORE REPORTING procedure the statement occurs.
- 4. This statement must be executed each time presentation of the report group is to be suppressed.
- 5. When a report group's presentation is suppressed, none of the following operations for the report will take place:
  - A. Actual presentation of the report group in question.
  - B. Processing of any LINE (see [LINE], page 167) clauses within the report group in question.
  - C. Processing of the NEXT GROUP (see [NEXT GROUP], page 170) clause (if any) within the report group in question.
  - D. Any modification to the LINE-COUNTER special register (see [Special Registers], page 227).
  - E. Any modification to the PAGE-COUNTER special register.

### **7.8.47. TERMINATE**

| TERMINATE Syntax       |  |  |
|------------------------|--|--|
| ERMINATE report-name-1 |  |  |
|                        |  |  |

The TERMINATE statement causes the processing of the specified report(s) to be completed.

- 1. Each report-name-1 must be the name of a report having an RD (see [REPORT SECTION], page 124) defined for it.
- 2. The specified report name(s) must be currently initiated (via INITIATE (see [INITIATE], page 296)) and cannot yet have been terminated.
- 3. The TERMINATE statement will present each CONTROL FOOTING (if any), in reverse sequence of the control hierarchy, starting with the most minor up to FINAL (if any). During the presentation of these groups and the processing of any USE BEFORE REPORTING procedures for those groups, the prior set of control data item values will be available, as though a control break had been detected at the most major control data name.
- 4. During the presentation of the CONTROL FOOTING groups, any necessary PAGE FOOTING and PAGE HEADING groups will be presented as well.
- 5. Finally, the REPORT FOOTING group, if any, will be presented.
- 6. If an INITIATE is followed by a TERMINATE with no intervening GENERATE (see [GENERATE], page 286) statements (all pertaining to the same report, of course), no report groups will be presented to the output file.

### **7.8.48. TRANSFORM**

### TRANSFORM Syntax TRANSFORM identifier-1 FROM { literal-1 } TO { literal-2 } ~~~~ { identifier-2 } ~~~ { identifier-3 }

The TRANSFORM statement scans a data item performing a series of mono-alphabetic substitutions, defined by the arguments before and after the TO clause.

- 1. Both literal-1 and/or literal-2 must be alphanumeric literals.
- 2. All of identifier-1, identifier-2 and identifier-3 must either be group items or alphanumeric data items. Numeric data items with a USAGE (see [USAGE], page 198) of DISPLAY are accepted, but will generate warning messages from the compiler.
- 3. The TRANSFORM statement will replace characters within *identifier-1* that are found in the string specified *before* the TO keyword with the corresponding characters from the string specified *after* the TO keyword.
- 4. This statement exists within GnuCOBOL to provide compatibility with COBOL programs written to pre-1985 standards. The TRANSFORM statement was made obsolete in the 1985 standard of COBOL, having been replaced by the CONVERTING clause of the INSPECT statement (see [INSPECT], page 297). New programs should be coded to use INSPECT CONVERTING rather than TRANSFORM.

### 7.8.49. UNLOCK

### **UNLOCK Syntax**

UNLOCK filename-1 RECORD|RECORDS

This statement synchronizes any as-yet unwritten file I/O buffers to the specified file (if any) and releases any record locks held for records belonging to file-name-1.

- 1. The reserved words RECORD and RECORDS are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. If file-name-1 is a Sort/Merge work file, no action will be taken.
- 3. Not all GnuCOBOL implementations support locking. Whether they do or not depends upon the operating system they were built for and the build options that were used when GnuCOBOL was generated. When a program using one of those GnuCOBOL implementations issues an UNLOCK, it will ignored. There will be no compiler message issued. Buffer syncing, if needed, will still occur.
- 4. See [Record Locking], page 54, for additional information on record locking.

### **7.8.50. UNSTRING**

### **UNSTRING Syntax**

The UNSTRING statement parses a string, extracting any number of sub strings from it.

- 1. The reserved words BY, IN and ON are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. identifier-1 through identifier-5 must be explicitly or implicitly defined with a USAGE (see [USAGE], page 198) of DISPLAY. Any of those identifiers may be group items.
- 3. Both literal-1 and literal-2 must be alphanumeric literals.
- 4. Each of identifier-6, identifier-7 and identifier-8 must be elementary non-edited integer numeric items.
- 5. At the time the UNSTRING statement begins execution, identifier-7 must have a value greater than 0.
- 6. identifier-1 will be referred to as the source string and each identifier-4 will be referred to as a destination field in the following discussions.
- 7. The UNSTRING statement's processing is based upon a *current character pointer*, the initial value of which will be the value of *identifier*-7 at the time the UNSTRING statement began execution. If no POINTER clause is coded, a value of 1 (meaning "the 1st character position") will be assumed for the current character pointer's initial value.
- 8. The source string will be parsed into sub strings starting from the current character pointer position. Sub strings are identified by using the various delimiter strings specified on the DELIMITED BY clause as inter-sub string separators.
- 9. Using the ALL option allows a delimiter sequence to be an arbitrarily long sequence of occurrences of the delimiter literal whereas its absence treats each occurrence as a separate delimiter. When multiple delimiters are specified, they will be looked for in the source string in the sequence in which they are coded.

- 10. Two consecutive delimiter sequences will identify a null sub string.
- 11. Identified sub strings will be moved into each destination field in the sequence they are identified; values moved into a destination field will be truncated if the sub string length exceeds the destination field length, or padded with spaces if the destination field length exceeds the sub string length. Both truncation and padding will be controlled by the presence or absence of a JUSTIFIED (see [JUSTIFIED], page 164) clause on the destination field.
- 12. Each destination field may have an optional DELIMITER clause. If a DELIMITER clause is specified, *identifier-5* will have the delimiter character string used to identify the sub string for the destination field moved into it. If a destination field was not altered (because an insufficient number of sub strings were identified), *identifier-5* for that destination field will also be unchanged.
- 13. Each destination field may have an optional COUNT clause. If a COUNT clause is specified, identifier-6 will have the size of the sub string (in characters) for the destination field moved into it. If a destination field was not altered (because an insufficient number of sub strings were identified), identifier-6 for that destination field will also be unchanged.
- 14. If a TALLYING clause is coded, *identifier-8* will be incremented by 1 each time a destination field is populated.
- 15. None of identifier-4, identifier-5, identifier-6, identifier-7 or identifier-8 are initialized by the UNSTRING statement. You need to do that yourself via a MOVE (see [MOVE], page 305) or INITIALIZE statement (see [INITIALIZE], page 292).
- 16. UNSTRING processing will cease when one of the following occurs:
  - A. The initial value of the current character pointer is less than 1 or greater than the number of character positions in *identifier-1*, or...
  - B. All destination fields have been fully processed
- 17. If event A occurs, none of the destination field contents (or the contents of their DELIMITER or COUNT identifiers) will be changed.
- 18. An *overflow* condition exists if either event A occurs, or if event B occurs with at least one character position in *identifier-1* not having been processed.
- 19. The optional ON OVERFLOW and NOT ON OVERFLOW clauses may be used to detect and react to the occurrence or not, respectively, of an overflow condition. See [ON OVERFLOW + NOT ON OVERFLOW], page 223, for additional information.

The following sample program illustrates the UNSTRING statement statement.

IDENTIFICATION DIVISION.

PROGRAM-ID. DEMOUNSTRING.

DATA DIVISION.

WORKING-STORAGE SECTION.

| 01 | Full-Name     | PIC X(40).   |
|----|---------------|--------------|
| 01 |               |              |
|    | 05 Last-Name  | PIC X(15).   |
|    | 05 First-Name | PIC X(15).   |
|    | 05 MI         | PIC X(1).    |
|    | 05 Delim-LN   | PIC X(1).    |
|    | 05 Delim-FN   | PIC X(1).    |
|    | 05 Delim-MI   | PIC X(1).    |
|    | 05 Count-LN   | BINARY-CHAR. |
|    | 05 Count-FN   | BINARY-CHAR. |
|    | 05 Count-MI   | BINARY-CHAR. |

```
05 Tallying-Ctr
 BINARY-CHAR.
 PROCEDURE DIVISION.
 P1. PERFORM UNTIL EXIT
 DISPLAY "Enter Full Name (null quits):"
 WITH NO ADVANCING
 ACCEPT Full-Name
 IF Full-Name = SPACES
 EXIT PERFORM
 END-IF
 INITIALIZE Parsed-Info
 UNSTRING Full-Name
 DELIMITED BY ", "
 OR ","
 OR ALL SPACES
 INTO Last-Name
 DELIMITER IN Delim-LN
 COUNT IN Count-LN
 First-Name
 DELIMITER IN Delim-FN
 COUNT IN Count-FN
 ΜI
 DELIMITER IN Delim-MI
 COUNT IN Count-MI
 TALLYING Tallying-Ctr
 DISPLAY "First-Name=" First-Name
 " Delim='" Delim-FN
"' Count=" Count-FN
 DISPLAY "MI =" MI "
 " Delim='" Delim-MI
"' Count=" Count-MI
 DISPLAY "Last-Name =" Last-Name
 " Delim='" Delim-LN
"' Count=" Count-LN
 DISPLAY "Tally= " Tallying-Ctr
 END-PERFORM
 DISPLAY "Bye!"
 STOP RUN
The following is sample output from the program:
 Enter Full Name (null quits):Cutler, Gary L
 First-Name=Gary

MI =L

Delim=', Count=+004

Delim=', Count=+001

Last-Name =Cutler

Delim=', Count=+006
 Tally= +003
 Enter Full Name (null quits):Snoddgrass,Throckmorton,P
 First-Name=Throckmorton Delim=',' Count=+012
 Delim=' ' Count=+001
 =P
 Last-Name =Snoddgrass Delim=',' Count=+010
 Tally= +003
 Enter Full Name (null quits):Munster Herman
```

Delim=' ' Count=+006

First-Name=Herman

```
MI = Delim=' ' Count=+000
Last-Name =Munster Delim=' ' Count=+007
Tally= +002
Enter Full Name (null quits):
Bye!
```

### 7.8.51. WRITE

### WRITE Syntax

```
WRITE record-name-1
 [FROM { literal-1
 }]
      ~~~~ { identifier-1 }
     [ WITH [ NO ] LOCK ]
     [ { BEFORE } ADVANCING { { literal-2
                                             } LINE|LINES } ]
      { ~~~~~ }
                            { { identifier-2
                                                           }
                            { PAGE
                                                           }
      { AFTER }
                            { ~~~~
                                                           }
                                                           }
                            { mnemonic-name-1
     [ AT END-OF-PAGE|EOP imperative-statement-1 ]
     [ NOT AT END-OF-PAGE|EOP imperative-statement-2 ]
     [ INVALID KEY imperative-statement-3 ]
     [ NOT INVALID KEY imperative-statement-4 ]
[ END-WRITE ]
```

The WRITE statement writes a new record to an open file.

- 1. The reserved words ADVANCING, AT, KEY, LINE, LINES and WITH are optional and may be omitted. The presence or absence of these words has no effect upon the program.
- 2. The reserved words END-OF-PAGE and EOP are interchangeable.
- 3. The record-name-1 specified on the statement must be defined as an 01-level record subordinate to the File Description (FD (see [File/Sort-Description], page 113)) of a file that is currently open for OUTPUT (see [File OPEN Modes], page 309), EXTEND or I-O.
- 4. The optional FROM clause will cause literal-1 or identifier-1 to be automatically moved into record-name-1 prior to writing record-name-1's contents to the appropriate file. If this clause is not specified, it is the programmer's responsibility to populate record-name-1 with the desired data prior to executing the WRITE.
- 5. The optional LOCK options may be used to manually control access to the just-written record by other programs while this program is running. See [Record Locking], page 54, to review the various record locking behaviour.
- 6. The optional INVALID KEY and NOT INVALID KEY clauses may be used when writing to relative or indexed files to detect and react to the failure (non-zero file status code) or success (00 file status code), respectively, of the statement. See [File Status Codes], page 98, for additional information.
- 7. When WRITE is used against an ORGANIZATION LINE SEQUENTIAL (see [ORGANIZATION LINE SEQUENTIAL], page 101) file, with or without the LINE ADVANCING (see [LINE AD-

VANCING], page 14) option, an end-of-record delimiter character sequence will be written to the file to signify where one record ends and the next record begins. This delimiter sequence will be either of the following:

- A line-terminator sequence consisting of an ASCII carriage-return/line-feed character sequence (X'ODOA') if you are running a MinGW or native Windows build of Gnu-COBOL
- A line-terminator sequence consisting of an ASCII line-feed character (X'OA') if you are running a Cygwin, Linux, Unix or OSX build of GnuCOBOL
- 8. The following points pertain to the use (or not) of the ADVANCING clause:
  - A. Using this clause with any organization other than ORGANIZATION LINE SEQUENTIAL will either be rejected outright by the compiler (relative or indexed files) or may introduce unwanted characters into the file (ORGANIZATION SEQUENTIAL (see [ORGANIZATION SEQUENTIAL], page 100)).
  - B. If no ADVANCING clause is specified on a WRITE to a line-advancing file, AFTER ADVANCING 1 LINE will be assumed; on other than line-advancing files, BEFORE ADVANCING 1 LINE will be assumed.
  - C. When BEFORE ADVANCING is used (or implied), the record is written to the file before the ADVANCING action writes line-terminator characters to the file.
  - D. If AFTER ADVANCING is used (or implied), the ADVANCING action writes line-terminator characters to the file and then the record data is written to the file.
  - E. The ADVANCING n LINES clause will introduce the specified number of line-terminator character sequences into the file either before the written record (AFTER ADVANCING) or after the written record (BEFORE ADVANCING).
  - F. If the LINAGE (see [File/Sort-Description], page 113) clause is absent from the file's FD:
    - a. The ADVANCING PAGE clause will introduce an ASCII formfeed character into the file either before the written record (AFTER PAGE) or after the written record (BEFORE PAGE).
    - b. Management of areas on the printed page such as top-of page headers, bottom-of-page footers, dealing with "full page" situations and the like are the complete responsibility of the programmer.
  - G. If the LINAGE clause is *present* in the file's FD:
    - a. The ADVANCING PAGE clause will introduce the appropriate number of line-terminator character sequences into the file either before the written record (AFTER ADVANCING) or after the written record (BEFORE ADVANCING) so as to force the printer to automatically advance to a new sheet of paper when the file prints. No formfeed characters will be generated when LINAGE is specified instead, it is assumed that the printer to which the report will be printed will be loaded with special forms that conform to the specifications defined by the LINAGE clause.
    - b. Management of areas on the printed page such as top-of page headers, bottom-of-page footers, dealing with "full page" situations and the like are now the joint responsibility of the programmer and the GnuCOBOL run-time library, which provides tools such as the LINAGE-COUNTER special register (see [Special Registers], page 227) and the END-OF-PAGE clause to deal with page formatting issues.
    - c. The AT END-OF-PAGE clause will be triggered, thus executing imperative-statement-1 (see [Imperative Statement], page 632), if the WRITE statement introduces a data line or line-feed character into the file at a line position within the Page Footer area defined by the LINAGE clause. The NOT AT END-OF-PAGE

clause will be triggered (thus executing *imperative-statement-2*) if no end-of-page condition occurred during the WRITE.

End of Chapter 7 — PROCEDURE DIVISION

### 8. Functions

### 8.1. Intrinsic Functions

GnuCOBOL supports a wide variety of "intrinsic functions" that may be used anywhere in the PROCEDURE DIVISION where a literal is allowed. For example:

```
MOVE FUNCTION LENGTH(Employee-Last-Name) TO Employee-LN-Len
```

Note how the word FUNCTION is part of the syntax when you use an intrinsic function. You can use intrinsic functions without having to include the reserved word FUNCTION via settings in the REPOSITORY (see [REPOSITORY], page 93) paragraph. You may accomplish the same thing by specifying the -fintrinsics switch to the GnuCOBOL compiler when you compile your programs.

User-written functions (see [Subprogram Types], page 603) never require the FUNCTION keyword when they are executed, because each user-written function a program uses *must* be included in that program's REPOSITORY paragraph, which therefore makes the FUNCTION keyword optional.

The following intrinsic functions, known to other "dialects" of COBOL, are defined to Gnu-COBOL as reserved words but are not otherwise implemented currently. Any attempts to use these functions will result in a compile-time error message. However they are described at the end of this chapter.

BOOLEAN-OF-INTEGER
CHAR-NATIONAL
DISPLAY-OF
EXCEPTION-FILE-N
EXCEPTION-LOCATION-N
INTEGER-OF-BOOLEAN
NATIONAL-OF
STANDARD-COMPARE

The supported intrinsic functions are listed in the following sections, along with their syntax and usage notes.


### 8.1.1. ABS

| ABS Function Syntax |  |  |
|---------------------|--|--|
| ABS(number)         |  |  |
|                     |  |  |

This function determines and returns the absolute value of number (a numeric literal or data item) supplied as an argument.

Note that  ${\tt ABSOLUTE-VALUE}$  has an alias for this function.

### 8.1.2. ACOS



The ACOS function determines and returns the trigonometric arc-cosine, or inverse cosine, of cosine value (a numeric literal or data item) supplied as an argument.

The result will be an angle, expressed in radians. You may convert this to an angle measured in degrees, as follows:

COMPUTE degrees = ( radians * 180 ) / FUNCTION PI

### **8.1.3.** ANNUITY

### **ANNUITY Function Syntax**

ANNUITY(interest-rate, number-of-periods)

This function returns a numeric value approximating the ratio of an annuity paid at *interest-rate* (numeric data item or literal) for each of *number-of-periods* (numeric data items or literals).

interest-rate is the rate of interest paid at each payment. If you only have an annual interest rate and you wish to compute monthly annuity payments, divide the annual interest rate by 12 and use that value for interest-rate.

Multiply the result of this function times the desired principal amount to determine the amount of each period's payment.

A note for the financially challenged: an annuity is basically a reverse loan; an accountant would take the result of this function multiplied by -1 times the principal amount to compute a loan payment you are making.

### 8.1.4. ASIN

## ASIN Function Syntax ASIN(sine)

The ASIN function determines and returns the trigonometric arc-sine, or inverse sine, of sine value (a numeric literal or data item) supplied as an argument.

The result will be an angle, expressed in radians. You may convert this to an angle measured in degrees, as follows:

COMPUTE degrees = ( radians * 180 ) / FUNCTION PI

### 8.1.5. ATAN

## ATAN (tangent)

Use this function to determine and return the trigonometric arc-tangent, or inverse tangent, of tangent value (a numeric literal or data item) supplied as an argument.

The result will be an angle, expressed in radians. You may convert this to an angle measured in degrees, as follows:

COMPUTE degrees = ( radians * 180 ) / FUNCTION PI

### 8.1.6. BYTE-LENGTH

### BYTE-LENGTH Function Syntax

BYTE-LENGTH(string)

BYTE-LENGTH returns the length — in bytes — of string (a group item, USAGE DISPLAY elementary item or alphanumeric literal). This intrinsic function is identical to the LENGTH-AN (see [LENGTH-AN], page 401) function. Note that the value returned by this function is not necessarily the number of characters comprising string, but rather the number of actual bytes required to store it.

For example, if *string* is encoded using a double-byte character set such as Unicode UTF-16 (where each character is represented by 16 bits of storage, not the 8-bits inherent to character sets like ASCII or EBCDIC), then calling this function with a *string* argument whose PICTURE (see [PICTURE], page 176) is X(4) would return a value of 8 rather than the value 4.

Contrast this with the LENGTH (see [LENGTH], page 400) function.

### 8.1.7. CHAR

## CHAR Function Syntax CHAR(integer)

This function returns the character in the ordinal position specified by *integer* (a numeric integer literal or data item with a value of 1 or greater) from the COLLATING SEQUENCE (see [OBJECT-COMPUTER], page 82) being used by the program.

For example, if the program is using the (default) ASCII character set, CHAR(34) returns the 34th character in the ASCII character set — an exclamation-point ('!'). If you are using this function to convert a numeric value to its corresponding ASCII character, you must use an argument value one greater than the numeric value.

If an argument whose value is less than 1 or greater than 256 is specified, the character in the program collating sequence corresponding to a value of all zero bits is returned.

The following code is an alternative approach when you just wish to convert a number to its ASCII equivalent:

```
O1 Char-Value.

O5 Numeric-Value USAGE BINARY-CHAR.

...

MOVE numeric-character-value TO Numeric-Value
```

The Char-Value item now has the corresponding ASCII character value.

### 8.1.8. COMBINED-DATETIME

### **COMBINED-DATETIME Function Syntax**

COMBINED-DATETIME(days, seconds)

This function returns a 12-digit numeric result, the first seven digits of which are the integer value of days argument (a numeric data item or literal) and the last five of which are the integer value of seconds argument (also a numeric data item or literal).

If days is less than 1 or greater than 3,067,671, or if seconds is less than 1 or greater than 86,400, a value of 0 is returned and a runtime error will result.

days Must be in integer date form. For details, see Integer date form. A value in integer date form is a positive integer that represents a number of days succeeding 31 December 1600, in the Gregorian calendar. It is based on a starting date of Monday, 1 January 1601 and integer date 1 represents Monday, 1 January 1601.

seconds Must be in standard numeric time form. For details, see Standard numeric time form. A value in standard numeric time form is a numeric value representing seconds past midnight.

The returned value is determined by arithmetic expression Days-1 + (Seconds-2/100000). The date occupies the integer part of the returned value and the time is represented in the fractional part of the returned value.

Example Given the integer date form value "143951", which represents the date 15 February 1995, and the standard numeric time form value "18867.812479168304", which represents the time "05:14:27.812479168304", the returned value would be exactly "143951.1886781247".

### 8.1.9. CONCATENATE

### CONCATENATE Function Syntax

CONCATENATE(string-1 [, string-2]...)

This function concatenates the *string-1*, *string-2*, . . . (group items, USAGE DISPLAY elementary items and/or alphanumeric literals) together into a single string result.

If a numeric literal or PIC 9 identifier is specified as an argument, decimal points, if any, will be removed and negative signs in PIC S9 fields or numeric literals will be inserted as defined by the SIGN IS (see [SIGN IS], page 190) clause (or absence thereof) of the field. Numeric literals are processed as if SIGN IS TRAILING SEPARATE were in effect.

### 8.1.10. COS



The COS function determines and returns the trigonometric cosine of angle (a numeric literal or data item) supplied as an argument.

angle is assumed to be a value expressed in radians. If you need to determine the cosine of an angle measured in degrees, you first need to convert that angle to radians as follows:

COMPUTE radians = ( degrees * FUNCTION PI) / 180

### 8.1.11. CURRENCY-SYMBOL

| CURRENCY-SYMBOL Function Syntax |  |  |
|---------------------------------|--|--|
| CURRENCY-SYMBOL                 |  |  |
|                                 |  |  |

The CURRENCY-SYMBOL function returns the currency symbol character currently in effect for the locale under which your program is running. On UNIX systems, your locale is established via the LANG run-time environment variable (see [Run Time Environment Variables], page 584) environment variable. On Windows, the Control Panel's "Regional and Language Options" define the locale.

Changing the currency symbol via the SPECIAL-NAMES (see [SPECIAL-NAMES], page 84) paragraph's CURRENCY SYMBOL setting will not affect the value returned by this function.

### 8.1.12. CURRENT-DATE

### **CURRENT-DATE** Function Syntax

CURRENT-DATE

Returns the current date and time as the following 21-character structure:

```
01 CURRENT-DATE-AND-TIME.
```

```
05 CDT-Year
                          PIC 9(4).
                          PIC 9(2). *> 01-12
05 CDT-Month
05 CDT-Day
                          PIC 9(2). *> 01-31
05 CDT-Hour
                          PIC 9(2). *> 00-23
                         PIC 9(2). *> 00-59
05 CDT-Minutes
                          PIC 9(2). *> 00-59
05 CDT-Seconds
05 CDT-Hundredths-Of-Secs PIC 9(2). *> 00-99
05 CDT-GMT-Diff-Hours
                         PIC S9(2)
                          SIGN LEADING SEPARATE.
05 CDT-GMT-Diff-Minutes
                          PIC 9(2). *> 00 or 30
```

Since this function has no arguments, no parenthesis should be specified.

### 8.1.13. DATE-OF-INTEGER

while DATE-OF-INTEGER (150000) returns 20110908.

### DATE-OF-INTEGER(integer)

This function returns a numeric calendar date in *yyyymmdd* (i.e. Gregorian) format. The date is determined by adding the number of days specified as *integer* (a numeric integer data item or literal) to the date December 31, 1600. For example, DATE-OF-INTEGER(1) returns 16010101

**DATE-OF-INTEGER Function Syntax** 

A value less than 1 or greater than 3067671 (9999/12/31) will return a result of 0.

DATE-TO-YYYYMMDD(yymmdd [, yy-cutoff [, yy-execution-time ]])

### 8.1.14. DATE-TO-YYYYMMDD

### DATE-TO-YYYYMMDD Function Syntax

~~~~~~~~~~

You can use this function to convert the six-digit Gregorian date specified as yymmdd (a numeric integer data item or literal) to an eight-digit format (yyyymmdd).

The optional yy-cutoff (a numeric integer data item or literal) argument is the year cutoff used to delineate centuries; if the year component of the date meets or exceeds this cutoff value, the result will be 19yymmdd; if the year component of the date is less than the cutoff value, the result will be 20yymmdd. The default cutoff value if no second argument is given will be 50.

The optional *yy-execution-time* argument (a numeric integer data item or literal) The default execution time value if no third argument is given will be now equivalent to specifying (FUNCTION NUMVAL (FUNCTION CURRENT-DATE (1:4))).

8.1.15. DAY-OF-INTEGER

DAY-OF-INTEGER Function Syntax DAY-OF-INTEGER(integer)

This function returns a calendar date in yyyyddd (i.e. Julian) format. The date is determined by adding the number of days specified as integer (a numeric integer data item or literal) to December 31, 1600. For example, DAY-OF-INTEGER(1) returns 1601001 while DAY-OF-INTEGER(250000) returns 2011251.

A value less than 1 or greater than 3067671 (9999/12/31) will return a result of 0.

8.1.16. DAY-TO-YYYYDDD

DAY-TO-YYYYDDD Function Syntax

DAY-TO-YYYYDDD(yyddd [, yy-cutoff [, yy-execution-time]])

You can use this function to convert the five-digit Julian date specified as yyddd (a numeric integer data item or literal) to a seven-digit numeric Julian format (yyyyddd).

The optional yy-cutoff argument (a numeric integer data item or literal) is the year cutoff used to delineate centuries; if the year component of the date meets or exceeds this cutoff value, the result will be 19yyddd; if the year component of the date is less than the cutoff, the result will be 20yyddd. The default cutoff value if no second argument is given will be 50.

The optional *yy-execution-time* argument (a numeric integer data item or literal) The default execution time value if no third argument is given will be now equivalent to specifying (FUNCTION NUMVAL (FUNCTION CURRENT-DATE (1:4))).

8.1.17. E

E Function Syntax E

This function returns the mathematical constant E (the base of natural logarithms). The maximum precision with which this value may be returned is 2.7182818284590452353602874713526625.

Since this function has no arguments, no parenthesis should be specified.

8.1.18. EXCEPTION-FILE

This function returns I/O exception information from the most-recently executed input or output statement. The information is returned as a 34-character string, where the first two characters are the two-digit file status value (see [File Status Codes], page 98) and the remaining 32 are the *file-name-1* specification from the file's SELECT (see [SELECT], page 95) statement.

The name returned after the file status information will be returned only if the returned file status value is not 00.

Since this function has no arguments, no parenthesis should be specified.

The documentation of the CBL\_ERROR\_PROC built-in system subroutine (see [CBL\_ERROR\_PROC], page 501) built-in subroutine illustrates the use of this function.

8.1.19. EXCEPTION-LOCATION

EXCEPTION-LOCATION Function Syntax

EXCEPTION-LOCATION

\_\_\_\_\_

This function returns exception information from the most-recently failing statement. The information is returned to a 1023 character string in one of the following formats, depending on the nature of the failure:

- primary-entry-point-name; paragraph OF section; statement-number
- primary-entry-point-name; section; statement-number
- primary-entry-point-name; paragraph; statement-number
- primary-entry-point-name; statement-number

Since this function has no arguments, no parenthesis should be specified.

The program must be compiled with the -debug switch, -ftraceall switch or -g switch for this function to return any meaningful information.

The documentation of the CBL\_ERROR\_PROC built-in system subroutine (see [CBL\_ERROR\_PROC], page 501) built-in subroutine illustrates the use of this function.

8.1.20. EXCEPTION-STATEMENT

EXCEPTION-STATEMENT Function Syntax EXCEPTION-STATEMENT

This function returns the most-recent COBOL statement that generated an exception condition. Since this function has no arguments, no parenthesis should be specified.

The program must be compiled with the <code>-debug</code> switch, <code>-ftraceall</code> switch or <code>-g</code> switch for this function to return any meaningful information.

The documentation of the CBL\_ERROR\_PROC built-in system subroutine (see [CBL\_ERROR\_PROC], page 501) built-in subroutine illustrates the use of this function.

8.1.21. EXCEPTION-STATUS

EXCEPTION-STATUS Function Syntax

EXCEPTION-STATUS

This function returns the error type (a text string — see column 2 of the upcoming table for the possible values) from the most-recent COBOL statement that generated an exception condition.

Since this function has no arguments, no parenthesis should be specified.

The documentation of the CBL\_ERROR\_PROC built-in system subroutine (see [CBL\_ERROR\_PROC], page 501) built-in subroutine illustrates the use of this function.

The following are the error type strings, and their corresponding exception codes and descriptions.

| Code | Error Type | Description |
|------|-------------------------|--|
| 0101 | EC-ARGUMENT-FUNCTION | Function argument error |
| 0202 | EC-BOUND-ODO | OCCURS DEPENDING ON data item out of bounds |
| 0204 | EC-BOUND-PTR | Data-pointer contains an address that is out of bounds |
| 0205 | EC-BOUND-REF-MOD | Reference modifier out of bounds |
| 0207 | EC-BOUND-SUBSCRIPT | Subscript out of bounds |
| 0303 | EC-DATA-INCOMPATIBLE | Incompatible data exception |
| 0500 | EC-I-0 | input-output exception |
| 0501 | EC-I-O-AT-END | I-O status 1x |
| 0502 | EC-I-0-E0P | An end of page condition occurred |
| 0504 | EC-I-O-FILE-SHARING | I-O status 6x |
| 0505 | EC-I-O-IMP | I-O status 9x |
| 0506 | EC-I-O-INVALID-KEY | I-O status 2x |
| 0508 | EC-I-O-LOGIC-ERROR | I-O status 4x |
| 0509 | EC-I-O-PERMANENT-ERROR | I-O status 3x |
| 050A | EC-I-O-RECORD-OPERATION | I-O status 5x |

| 0601 | EC-IMP-ACCEPT | Implementation-defined accept condition |
|------|-----------------------|--|
| 0602 | EC-IMP-DISPLAY | Implementation-defined display condition |
| OAOO | EC-OVERFLOW | Overflow condition |
| 0A02 | EC-OVERFLOW-STRING | STRING overflow condition |
| 0A03 | EC-OVERFLOW-UNSTRING | UNSTRING overflow condition |
| 0B05 | EC-PROGRAM-NOT-FOUND | Called program not found |
| 0D03 | EC-RANGE-INSPECT-SIZE | Size of replace item in inspect differs |
| 1000 | EC-SIZE | Size error exception |
| 1004 | EC-SIZE-OVERFLOW | Arithmetic overflow in calculation |
| 1005 | EC-SIZE-TRUNCATION | Significant digits truncated in store |
| 1007 | EC-SIZE-ZERO-DIVIDE | Division by zero |
| 1202 | EC-STORAGE-NOT-ALLOC | The data-pointer specified in a FREE statement does not identify currently allocated storage |
| 1203 | EC-STORAGE-NOT-AVAIL | The amount of storage requested by an ALLOCATE statement is not available |

8.1.22. EXP

| | EXP Function Syntax | |
|-------------|---------------------|--|
| EXP(number) | | |
| | | |

Computes and returns the value of the mathematical constant e raised to the power specified by number (a numeric literal or data item).

8.1.23. EXP10

| | EXP10 Function Syntax |
|---------------|-----------------------|
| EXP10(number) | |
| | |

Computes and returns the value of 10 raised to the power specified by number (a numeric literal or data item).

8.1.24. FACTORIAL

| | FACTORIAL Function Syntax |
|-------------------|---------------------------|
| FACTORIAL(number) | |
| | |

This function computes and returns the factorial value of number (a numeric literal or data item).

8.1.25. FORMATTED-CURRENT-DATE

FORMATTED-CURRENT-DATE Function Syntax FORMATTED-CURRENT-DATE (argument-1)

FORMATTED-CURRENT-DATE returns the current date and time provided by the system at run-time, formatted according to date-and-time-format according to the argument type.

The function argument must be a national or alphanumeric literal and the content, a combined date and time format.

The returned value is formatted to the same form as argument-1.

8.1.26. FORMATTED-DATE

FORMATTED-DATE Function Syntax

FORMATTED-DATE (argument-1, argument-2)

FORMATTED-DATE uses a format to convert a date in integer date form to a date in the requested

argument-1 shall be a national or alphanumeric literal.

argument-2 shall be a value in integer date form.

format. The returned value will be in date format.

8.1.27. FORMATTED-DATETIME

FORMATTED-DATETIME Function Syntax

FORMATTED-DATETIME (argument-1, argument-2, argument-3, argument-4)

FORMATTED-DATETIME uses a combined time and date form to convert and combine a date in integer form and a numeric time expressed as seconds past midnight in UTC.

argument-1 shall be a national or alphanumeric literal.

argument-2 shall be a value in integer date form.

argument-3 shall be a value in standard numeric time form.

argument-4 is an integer specifying the offset from UTC expressed in minutes. If specified but have a value equal or less than 1439.

Note: The offset value 1439 represents 23 hours 59 minutes which is one minutes less than a day.

argument-4 must not be specified if the time portion in argument-1 is neither a UTC nor an offset format.

The returned value is a representation of the date contained in argument-2 combined with the time contained in argument-3 according to the format in argument-1.

If the format in argument-1 indicates that the returned value is to be expressed in UTC, the time portion of the returned value reflects the adjustment of the value in argument-3 by the offset in argument-4.

If the format in argument-1 indicates that the time is to be returned as an offset from UTC, the value in argument-3 is reflected directly in the time portion of the returned value and the offset in argument-4 is reflected directly in the offset portion of the returned value.

8.1.28. FORMATTED-TIME

FORMATTED-TIME Function Syntax

FORMATTED-TIME (argument-1, argument-2, argument-3)

FORMATTED-TIME converts a value representing seconds past midnight formatted time of day with optional offset.

argument-1 shall be a national or alphanumeric literal.

argument-2 shall be a value in integer time form.

argument-3 is an integer specifying the offset from UTC expressed in minutes. If specified but have a value equal or less than 1439.

Note: The offset value 1439 represents 23 hours 59 minutes which is one minutes less than a day.

argument-3 must not be specified if the time portion in argument-1 is neither a UTC nor an offset format.

Returned value:

Is a representation of the standard numeric time contained in argument-2 according to the format in argument-1.

If the format in argument-1 indicates that the returned value is to be expressed in UTC, the time portion of the returned value reflects the adjustment of the value in argument-2 by the offset in argument-3.

If the format in argument-1 indicates that the time is to be returned as an offset from UTC, the value in argument-2 is reflected directly in the time portion of the returned value and the offset in argument-3 is reflected directly in the offset portion of the returned value.

8.1.29. FRACTION-PART

| | FRACTION-PART Function Syntax |
|-----------------------|-------------------------------|
| FRACTION-PART(number) | |
| | |

This function returns that portion of *number* (a numeric data item or a numeric literal) that occurs to the right of the decimal point. FRACTION-PART(3.1415), for example, returns a value of 0.1415. This function is equivalent to the expression:

number -- FUNCTION INTEGER-PART(number)

8.1.30. HIGHEST-ALGEBRAIC

| HIGHEST-ALGEBRAIC Function Syntax |
|---------------------------------------|
| HIGHEST-ALGEBRAIC(numeric-identifier) |
| |

This function returns the highest (i.e. largest or farthest away from 0 in a positive direction if numeric-identifier is signed) value that could possibly be stored in numeric-identifier.

8.1.31. INTEGER

| | INTEGER Function Syntax |
|-----------------|-------------------------|
| INTEGER(number) | |
| | |

The INTEGER function returns the greatest integer value that is less than or equal to number (a numeric literal or data item).

8.1.32. INTEGER-OF-DATE

INTEGER-OF-DATE function Syntax INTEGER-OF-DATE(date)

This function converts date (a numeric integer data item or literal) — presumed to be a Gregorian calendar form standard date (YYYYMMDD) — to internal date form (the number of days that have transpired since 1600/12/31).

Once in that form, mathematical operations may be performed against the internal date before it is transformed back into a date using the DATE-OF-INTEGER (see [DATE-OF-INTEGER], page 376) or DAY-OF-INTEGER (see [DAY-OF-INTEGER], page 378) function.

8.1.33. INTEGER-OF-DAY

INTEGER-OF-DAY Function Syntax INTEGER-OF-DAY(date)

This function converts date (a numeric integer data item or literal) — presumed to be a Julian calendar form standard date (YYYYDDD) — to internal date form (the number of days that have transpired since 1600/12/31).

Once in that form, mathematical operations may be performed against the internal date before it is transformed back into a date using the DATE-OF-INTEGER (see [DATE-OF-INTEGER], page 376) or DAY-OF-INTEGER (see [DAY-OF-INTEGER], page 378) function.

8.1.34. INTEGER-OF-FORMATTED-DATE

INTEGER-OF-FORMATTED-DATE Function Syntax

INTEGER-OF-FORMATTED-DATE (argument-1, argument-2)

INTEGER-OF-FORMATTED-DATE converts a date that is in specified format to integer date form.

argument-1 shall be a national or alphanumeric literal. The content must be either a date format or a combined date and time format.

argument-2 shall be a data item of the same type as argument-1.

If argument-1 is a date format the content of argument-2 shall be a valid date in that format.

If argument-1 is a combined date and time format, the content of argument-2 shall be a valid combined date and time in same format.

8.1.35. INTEGER-PART

| | INTEGER-PART Function Syntax |
|--------------------------------|---|
| INTEGER-PART(number) | |
| Returns the integer portion of | of number (a numeric literal or data item). |

8.1.36. LENGTH

LENGTH Function Syntax LENGTH(string)

Returns the length — in characters — of *string* (a group item, USAGE DISPLAY elementary item or alphanumeric literal).

The value returned by this function is not the number of bytes of storage occupied by string, but rather the number of actual characters making up the string. For example, if string is encoded using a double-byte character set such as Unicode UTF-16 (where each character is represented by 16 bits of storage, not the 8-bits inherent to character sets like ASCII or EBCDIC), then calling this function with a string argument whose PICTURE is X(4) would return a value of 4 rather than the value 8 (the actual number of bytes of storage occupied by that item).

Contrast this function with the BYTE-LENGTH (see [BYTE-LENGTH], page 369) and LENGTH-AN (see [LENGTH-AN], page 401) functions.

8.1.37. LENGTH-AN

LENGTH-AN(string)

This function returns the length — in bytes of storage — of string (a group item, USAGE DISPLAY elementary item or alphanumeric literal).

This intrinsic function is identical to the BYTE-LENGTH (see [BYTE-LENGTH], page 369) function.

Note that the value returned by this function is not the number of *characters* making up the *string*, but rather the number of actual *bytes* of storage required to store *string*. For example, if *string* is encoded using a double-byte character set such as Unicode UTF-16 (where each character is represented by 16 bits of storage, not the 8-bits inherent to character sets like ASCII or EBCDIC), then calling this function with a *string* argument whose PICTURE is X(4) would return a value of 8 rather than the value 4.

Contrast this with the LENGTH (see [LENGTH], page 400) function.

8.1.38. LOCALE-COMPARE

LOCALE-COMPARE Function Syntax

LOCALE-COMPARE(argument-1, argument-2 [, locale])

The LOCALE-COMPARE function returns a character indicating the result of comparing argument-1 and argument-2 using a culturally-preferred ordering defined by a locale.

Either or both of the 1<sup>st</sup> two arguments may be an alphanumeric literal, a group item or an elementary item appropriate to storing alphabetic or alphanumeric data. If the lengths of the two arguments are unequal, the shorter will be assumed to be padded to the right with spaces.

The two arguments will be compared, character by character, against each other until their relationship to each other can be determined. The comparison is made according to the cultural rules in effect for *locale* name or for the current locale if no *locale* argument is specified. Once that relationship is determined, a one-character alphanumeric value will be returned as follows:

- '<' If argument-1 is determined to be less than argument-2
- '=' If the two arguments are equal to each other
- '>' If argument-1 is determined to be greater than argument-2

See [LOCALE Names], page 85, for a list of typically-available locale names.

8.1.39. LOCALE-DATE

LOCALE-DATE Function Syntax LOCALE-DATE(date [, locale])

Converts the eight-digit Gregorian date (a numeric integer data item or literal) from yyyymmdd format to the format appropriate to the current locale. On a Windows system, this will be the "short date" format as set using Control Panel.

You may include an optional second argument to specify the *locale* name (group item or PIC X identifier) you'd like to use for date formatting. If used, this second argument *must* be an identifier. Locale names are specified using UNIX-standard names.

8.1.40. LOCALE-TIME

LOCALE-TIME Function Syntax

LOCALE-TIME(time [, locale])

Converts the four- (hhmm) or six-digit (hhmmss) time (a numeric integer data item or literal) to a format appropriate to the current locale. On a Windows system, this will be the "time"

format as set using Control Panel.

You may include an optional locale name (a group item or PIC X identifier) you'd like to use for time formatting. If used, this second argument must be an identifier. Locale names are specified using UNIX-standard names.

8.1.41. LOCALE-TIME-FROM-SECONDS

LOCALE-TIME-FROM-SECONDS Function Syntax

LOCALE-TIME-FROM-SECONDS(seconds [, locale])

Converts the number of seconds since midnight (a numeric integer data item or literal) to a format appropriate to the current locale. On a Windows system, this will be the "time" format as set using Control Panel.

You may include an optional locale name (a group item or PIC X identifier) you'd like to use for time formatting. If used, this second argument must be an identifier. Locale names are specified using UNIX-standard names.

See [LOCALE Names], page 85, for a list of typically-available locale names.

8.1.42. LOG

| | LOG Function Syntax | |
|-------------|---------------------|--|
| LOG(number) | | |
| | | |

Computes and returns the natural logarithm (base e) of number (a numeric literal or data item).

8.1.43. LOG10

| | LOG10 Function Syntax | |
|---------------|-----------------------|--|
| LOG10(number) | | |
| | | |

Computes and returns the base 10 logarithm of *number* (a numeric literal or data item).

8.1.44. LOWER-CASE

| | LOWER-CASE Function Syntax |
|--------------------|----------------------------|
| LOWER-CASE(string) | |
| | |

This function returns the value of *string* (a group item, USAGE DISPLAY elementary item or alphanumeric literal), converted entirely to lower case.

What constitutes a "letter" (or upper/lower case too, for that manner) may be influenced through the use of a CHARACTER CLASSIFICATION (see [OBJECT-COMPUTER], page 82).

8.1.45. LOWEST-ALGEBRAIC

LOWEST-ALGEBRAIC (numeric-identifier)

This function returns the lowest (i.e. smallest or farthest away from 0 in a negative direction if numeric-identifier is signed) value that could possibly be stored in numeric-identifier.

8.1.46. MAX

MAX Function Syntax MAX(number-1 [, number-2]...)

This function returns the maximum value from the specified list of numbers (each number-n may be a numeric data item or a numeric literal).

8.1.47. MEAN

MEAN Function Syntax MEAN(number-1 [, number-2]...)

This function returns the statistical mean value of the specified list of numbers (each *number-n* may be a numeric data item or a numeric literal).

8.1.48. MEDIAN

MEDIAN (number-1 [, number-2]...)

This function returns the statistical median value of the specified list of numbers (each *number-n* may be a numeric data item or a numeric literal).

8.1.49. MIDRANGE

MIDRANGE Function Syntax MIDRANGE(number-1 [, number-2]...)

The MIDRANGE (middle range) function returns a numeric value that is the arithmetic mean (average) of the values of the minimum and maximum numbers from the supplied list. Each number-n may be a numeric data items or a numeric literal.

8.1.50. MIN

MIN Function Syntax MIN(number-1 [, number-2]...)

This function returns the minimum value from the specified list of numbers (each *number-n* may be a numeric data item or a numeric literal).

8.1.51. MOD

| | MOD Function Syntax | |
|---------------------|---------------------|--|
| MOD(value, modulus) | | |

This function returns the value of *value* modulo *modulus* (essentially the remainder from the division of *value* by *modulus*). Both arguments may be numeric data items or numeric literals. Either (or both) may have a non-integer value.

8.1.52. MODULE-CALLER-ID

MODULE-CALLER-ID Function Syntax MODULE-CALLER-ID

This function returns the null string if it is executed within a main program. When executed with a subprogram, it returns the entry-point name of the program that called the subprogram.

The discussion of the MODULE-TIME (see [MODULE-TIME], page 422) function includes a sample program that uses this function.

Since this function has no arguments, no parenthesis should be specified.

8.1.53. MODULE-DATE

| MODULE-DATE Function Syntax | | | | |
|-----------------------------|--|--|--|--|
| MODULE-DATE | | | | |
| | | | | |

This function Returns the date the GnuCOBOL program that is executing the function was compiled, in the form yyyymmdd.

The discussion of the ${\tt MODULE-TIME}$ (see [MODULE-TIME], page 422) function includes a sample program that uses this function.

Since this function has no arguments, no parenthesis should be specified.

8.1.54. MODULE-FORMATTED-DATE

MODULE-FORMATTED-DATE

MODULE-FORMATTED-DATE Function Syntax

This function returns the fully-formatted date and time when the program executing the function was compiled. The exact format of this returned string value may vary depending on the operating system and GnuCOBOL build type.

The discussion of the MODULE-TIME (see [MODULE-TIME], page 422) function includes a sample program that uses this function.

Since this function has no arguments, no parenthesis should be specified.

8.1.55. MODULE-ID

| | MODULE-ID Function Syntax |
|-----------|---------------------------|
| MODULE-ID | |
| | |

This function returns the primary entry-point name (i.e. the PROGRAM-ID or FUNCTION-ID of the program. See [IDENTIFICATION DIVISION], page 77, for information on those clauses.

The discussion of the MODULE-TIME (see [MODULE-TIME], page 422) function includes a sample program that uses this function.

8.1.56. MODULE-PATH

MODULE-PATH Function Syntax MODULE-PATH

This function returns the full path to the executable version of this GnuCOBOL program. The filename component of this value will be exactly as typed on the command line, down to the use of upper- and lower-case letters and presence (or absence) of any extension.

The discussion of the MODULE-TIME (see [MODULE-TIME], page 422) function includes a sample program that uses this function.

8.1.57. MODULE-SOURCE

MODULE-SOURCE MODULE-SOURCE

The filename of the source code of the program (as specified on the cobc command when the program was compiled) is returned by this function.

The discussion of the MODULE-TIME (see [MODULE-TIME], page 422) function includes a sample program that uses this function.

8.1.58. MODULE-TIME

MODULE-TIME Function Syntax

MODULE-TIME

\_\_\_\_\_

This function returns the time the GnuCOBOL program was compiled, in the form hhmmss.

Since this function has no arguments, no parenthesis should be specified.

```
The following sample program uses all the MODULE- Functions:
  IDENTIFICATION DIVISION.
  PROGRAM-ID. DEMOMODULE.
  ENVIRONMENT DIVISION.
  CONFIGURATION SECTION.
  REPOSITORY.
      FUNCTION ALL INTRINSIC.
  PROCEDURE DIVISION.
  000-Main.
      DISPLAY "MODULE-CALLER-ID = [" MODULE-CALLER-ID ']'
      DISPLAY "MODULE-DATE = [" MODULE-DATE ']'
      DISPLAY "MODULE-FORMATTED-DATE = [" MODULE-FORMATTED-DATE ']'
      DISPLAY "MODULE-ID = [" MODULE-ID ']'
      DISPLAY "MODULE-PATH
                                  = [" MODULE-PATH ']'
                                = [" MODULE-SOURCE ']'
      DISPLAY "MODULE-SOURCE
      DISPLAY "MODULE-TIME
                                   = [" MODULE-TIME ']'
      STOP RUN
```

The program produces this output when executed:

```
MODULE-CALLER-ID = []
MODULE-DATE = [20180522]
MODULE-FORMATTED-DATE = [May 22 2018 12:43:14]
MODULE-ID = [DEMOMODULE]
MODULE-PATH = [/home/vince/cobolsrc/ACAS/demomodule]
MODULE-SOURCE = [demomodule.cbl]
MODULE-TIME = [124314]
```

8.1.59. MONETARY-DECIMAL-POINT

MONETARY-DECIMAL-POINT Function Syntax

MONETARY-DECIMAL-POINT

\_\_\_\_

MONETARY-DECIMAL-POINT returns the character used to separate the integer portion from the fractional part of a monetary currency value according to the rules currently in effect for the locale under which your program is running.

On UNIX (including OSX, Windows/Cygwin and Windows/MinGW) systems, your locale is established via the LANG run-time environment variable (see [Run Time Environment Variables], page 584) environment variable. On Windows, the Control Panel's Regional and Language Options define the locale.

Using the DECIMAL-POINT IS COMMA (see [SPECIAL-NAMES], page 84) clause in your program will not affect the value returned by this function.

is running.

8.1.60. MONETARY-THOUSANDS-SEPARATOR

MONETARY-THOUSANDS-SEPARATOR Function Syntax

MONETARY-THOUSANDS-SEPARATOR

This function returns the character used to separate the thousands digit groupings of monetary currency values according to the rules currently in effect for the locale under which your program

On UNIX (including OSX, Windows/Cygwin and Windows/MinGW) systems, your locale is established via the LANG run-time environment variable (see [Run Time Environment Variables], page 584) environment variable. On Windows, the Control Panel's Regional and Language Options define the locale.

Using the DECIMAL-POINT IS COMMA (see [SPECIAL-NAMES], page 84) clause in your program will not affect the value returned by this function.

8.1.61. NUMERIC-DECIMAL-POINT

NUMERIC-DECIMAL-POINT

This function returns the character used to separate the integer portion of a non-integer numeric item from the fractional part according to the rules currently in effect for the locale under which your program is running.

NUMERIC-DECIMAL-POINT Function Syntax

On UNIX (including OSX, Windows/Cygwin and Windows/MinGW) systems, your locale is established via the LANG run-time environment variable (see [Run Time Environment Variables], page 584) environment variable. On Windows, the Control Panel's Regional and Language Options define the locale.

Using the DECIMAL-POINT IS COMMA (see [SPECIAL-NAMES], page 84) clause in your program will not affect the value returned by this function.

8.1.62. NUMERIC-THOUSANDS-SEPARATOR

NUMERIC-THOUSANDS-SEPARATOR Function Syntax

NUMERIC-THOUSANDS-SEPARATOR

\_\_\_\_

This function returns the character used to separate the thousands digit groupings of numeric values according to the rules currently in effect for the locale under which your program is running.

On UNIX (including OSX, Windows/Cygwin and Windows/MinGW) systems, your locale is established via the LANG run-time environment variable (see [Run Time Environment Variables], page 584) environment variable. On Windows, the Control Panel's Regional and Language Options define the locale.

Using the DECIMAL-POINT IS COMMA (see [SPECIAL-NAMES], page 84) clause in your program will not affect the value returned by this function.

8.1.63. NUMVAL

NUMVAL Function Syntax

NUMVAL(string)

The NUMVAL function converts a *string* (a group item, USAGE DISPLAY elementary item or alphanumeric literal) to its corresponding numeric value.

The *string* must have any of the following formats, where '#' represents a sequence of one or more decimal digits:

There must be at least one digit character in the string.

Leading and/or trailing spaces are allowed, as are spaces before the first digit.

The character period in argument-1 string, represents the decimal separator. The character comma in argument-1 represents the grouping separator. When the DECIMAL-POINT IS COMMA clause is specified, the character comma shall be used in argument-1 to represent the decimal separator and the character period shall be used to represent the grouping separator.

Note: Locale-based functionality equivalent to NUMVAL can be obtained by using the NUMVAL-C function with the LOCALE keyword. A currency sign is optional in NUMVAL-C. The locale category LC\_MONETARY will be used because there is no sign convention specified in locale category LC\_NUMERIC.

Returned values:

The returned value is the numeric value represented by string.

If it contains a CR, DB, or the minus sign ('-'), the returned value is negative.

8.1.64. NUMVAL-C

NUMVAL-C Function Syntax

This function converts a *string* (a group item, USAGE DISPLAY elementary item or alphanumeric literal) representing a currency value to its corresponding numeric value.

The currency string if any, and any grouping separators preceding the decimal separator are ignored. Optionally, the currency string, sign convention, grouping separator and the decimal separator permitted in the character string may be specified by locale category LC-MONETARY, or the currency string may be specified by symbol.

The optional symbol character represents the currency symbol (a non-space single-character group item, USAGE DISPLAY elementary item or alphanumeric literal) that may be used as the currency character in string. Any spaces including leading or trailing are ignored. If no symbol is specified, the value that would be returned by the CURRENCY-SYMBOL intrinsic function (see [CURRENCY-SYMBOL], page 374) will be used.

If this references the LOCALE:

Changing the currency symbol via the SPECIAL-NAMES paragraph's CURRENCY SYMBOL setting will not affect the value returned by this function.

While NUMVAL-C will always use the currency symbol that is specified via the SPECIAL-NAMES paragraph's CURRENCY SYMBOL (or the system default which is currently always '\$').

string may have any of the following formats, where '#' represents a sequence of one or more decimal digits and '\$' represents the symbol character:

```
# -# +# #- #+ #CR #DB

#.# -#.# +#.# #.#- #.#+ #.#CR #.#DB

$# -$# +$# $#- $#+ $#CR $#DB

$#.# -$#.# +$#.# $#.#- $#.#+ $#.#CR $#.#DB
```

There must be at least one digit character in the string.

Leading and/or trailing spaces are allowed, as are spaces before and/or after the currency symbol, sign, CR and DB characters.

If the ANYCASE keyword is used the matching rules for detecting a currency string in argument- 1 are case-insensitive. If the ANYCASE keyword is not specified, the matching rules are case-sensitive.

If neither symbol nor the LOCALE keyword is specified, there shall be only one currency string used, either the default currency sign or a currency string specified in the SPECIAL-NAMES paragraph.

The returned value is the numeric value represented by string.

When the LOCALE keyword is specified, the returned value is negative if string contains a negative sign.

When the LOCALE keyword is not specified, the returning value is negative if string contains CR, DB, or a minus sign.

8.1.64B. NUMVAL-C-V2

NUMVAL-C function Syntax NUMVAL-C (argument-1 [, argument-2] [, LOCALE locale-name-1] [, ANYCASE])

This function returns the numeric value represented by the character string specified by argument-1 and defined as alphanumeric.

argument-2, the currency string if any, and any grouping separators preceding the decimal separator are ignored. Optionally, the currency string, sign convention, grouping separator and the decimal separator permitted in the character string may be specified by locale category LC-MONETARY, or the currency string may be specified by argument-2.

The optional alphanumeric argument-2 character represents the currency symbol (a non-space and at least one single-character item, that may be used as the currency character in argument-1. Any spaces including leading or trailing are ignored. If no argument-2 is specified, the value that would be returned by the CURRENCY-SYMBOL intrinsic function (see [CURRENCY-SYMBOL], page 374) will be used. argument-2 must not contain any of the digits - through 9, characters '\*', '+', '-', ',' or '.'; or the two consecutive letters CR or DB, whether upper or lower case or a combination of both.

argument-2 specifies a currency string that may appear in argument-1.

If the ANYCASE keyword is specified, the matching rules for detecting a currency string in argument-1 are case-insensitive. If not specified, the matching rules are case-sensitive.

If neither argument-2 nor the LOCALE keyword is specified, there shall be only one currency string used, either the default currency sign or a currency string specified in the SPECIAL-NAMES paragraph.

While NUMVAL-C will always use the currency symbol that is specified via the SPECIAL-NAMES paragraph's CURRENCY SYMBOL (or the system default which is currently always '\$') argument-1 shall have any of the following formats, where '#' represents a sequence of one or more decimal digits and '\$' represents the symbol character:

```
# -# +# #- #+ #CR #DB

#.# -#.# +#.# #.#- #.#+ #.#CR #.#DB

$# -$# +$# $#- $#+ $#CR $#DB

$#.# -$#.# +$#.# $#.#- $#.#+ $#.#CR $#.#DB
```

There must be at least one digit character in the string.

Leading and/or trailing spaces are allowed, as are spaces before and/or after the currency symbol, sign, CR and DB characters.

The returned value is the numeric value represented by argument-1.

When the LOCALE keyword is specified, the returned value is negative if string contains a negative sign and when not specified, the returning value is negative if string contains CR, DB, or a minus sign.

8.1.65. NUMVAL-F

NUMVAL-F Function Syntax

NUMVAL-F(char)

This function converts a *string* (a group item, USAGE DISPLAY elementary item or alphanumeric literal) representing a floating-point value to its corresponding numeric value.

```
# -# +# #E# -#E# +#E#

#E+# -#E+# +#E+# #E-# -#E-# +#E-#

#.# -#.# +#.# #.#E# -#.#E# +#.#E#

#.#E+# -#.#E+# +#.#E-# -#.#E-# +#.#E-#
```

There must be at least one digit character both before and after the E in the string.

Leading and/or trailing spaces are allowed, as are spaces before and/or after any sign characters.

8.1.66. ORD

ORD Function Syntax ORD(char)

This function returns the ordinal position in the program character set (usually ASCII) corresponding to the 1<sup>st</sup> character of *char* argument (a group item, USAGE DISPLAY elementary item or alphanumeric literal).

For example, assuming the program is using the standard ASCII collating sequence, ORD('!') returns 34 because '!' is the 34th ASCII character. If you are using this function to convert an ASCII character to its numeric value, you must subtract one from the result.

The following code is an alternative approach when you just wish to convert an ASCII character to its numeric equivalent:

```
01 Char-Value.
05 Numeric-Value USAGE BINARY-CHAR.
...
MOVE "character" TO Char-Value
Numeric-Value now has the numeric value of character.
```

8.1.67. ORD-MAX

ORD-MAX Function Syntax

ORD-MAX(char-1 [, char-2]...)

This function returns the ordinal position in the argument list corresponding to the *char-n* whose 1<sup>st</sup> character has the highest position in the program collating sequence (usually ASCII).

For example, assuming the program is using the standard ASCII collating sequence, ORD-MAX('Z', 'z', '!') returns 2 because the 2nd character in the argument list (the ASCII character 'z') occurs after 'Z' and '!' in the program collating sequence. Each *char-n* argument may be a group item, USAGE DISPLAY elementary item or alphanumeric literal.

8.1.68. ORD-MIN

ORD-MIN(char-1 [, char-2]...)

This function returns the ordinal position in the argument list corresponding to the *char-n* whose 1<sup>st</sup> character has the lowest position in the program collating sequence (usually ASCII).

For example, assuming the program is using the standard ASCII collating sequence, ORD-MIN('Z', 'z', '!') returns 3 because the 3rd character in the argument list (the ASCII character '!') occurs before 'Z' and 'z' in the program collating sequence. Each *char-n* argument may be a group item, USAGE DISPLAY elementary item or alphanumeric literal.

8.1.69. PI

| | PI Function Syntax | |
|----|--------------------|--|
| PI | | |
| ~~ | | |
| | | |

This function returns the mathematical constant PI. The maximum precision with which this value may be returned is 3.1415926535897932384626433832795029.

8.1.70. PRESENT-VALUE

PRESENT-VALUE Function Syntax

PRESENT-VALUE(rate, value-1 [, value-2])

The PRESENT-VALUE function returns a value that approximates the present value of a series of future period-end amounts specified by the various *value-n* arguments at a discount rate specified by the *rate* argument.

All arguments are numeric data items and/or numeric literals.

The following equation summarizes how present value is calculated, where N is the number of value arguments:

$$present value = \sum_{i=1}^{N} \left(\frac{value_i}{(1 + rate)^i} \right)$$

8.1.71. RANDOM

RANDOM Function Syntax

RANDOM[(seed)]

\_\_\_\_\_

This function returns a pseudo-random non-integer value in the range 0 to 1 (for example, 0.123456789).

The purpose of the optional seed argument, is to initialize the chain of pseudo-random numbers that will be returned by the function. Not only will calls to this function using the same seed value return the same pseudo-random number, but so will all subsequent executions of the function without a seed. This is actually a good thing when you are testing your program because you can rely on always receiving the same sequence of "random" numbers if you always start using the same seed.

The seed may be any form of literal or data item. If seed is numeric, its numeric value will serve as the seed value. If seed is alphanumeric, a value for it will be determined as if it were used as an argument to NUMVAL (see [NUMVAL], page 427).

Take, for example, the following sample program:

```
IDENTIFICATION DIVISION.
PROGRAM-ID. DEMORANDOM.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 Pseudo-Random-Number
                                USAGE COMP-1.
PROCEDURE DIVISION.
000-Main.
    MOVE FUNCTION RANDOM(1) TO Pseudo-Random-Number
    DISPLAY Pseudo-Random-Number
    PERFORM 4 TIMES
        MOVE FUNCTION RANDOM
                                 TO Pseudo-Random-Number
        DISPLAY Pseudo-Random-Number
    END-PERFORM
    STOP RUN
```

Every time this program is executed, it will produce the same output, because the same sequence of pseudo-random numbers will be generated:

- 0.41
- 0.18467
- 0.63340002
- 0.26499999
- 0.19169

It is worth mentioning that if the *first* execution of RANDOM in your program lacks a *seed* argument, the result will be exactly as if that execution were coded with a *seed* argument value of 1.

Once your program has been thoroughly tested, you'll want different sequences to be generated each time the program runs. One possible way to accomplish this is to use a *seed* that is likely to be different every time the program is executed, as is likely to be the case if the first MOVE statement in the previous example were replaced by this:

MOVE RANDOM(FUNCTION CURRENT-DATE(1:16))

TO Pseudo-Random-Number

The first 16 characters returned by the CURRENT-DATE (see [CURRENT-DATE], page 375) function will be a number in the format YYYYMMDDhhmmssnn, where YYYYMMDD is the current calendar date and hhmmssnn is the current time of day to the one one-hundredth of a second. Since two different executions of the program will never get identical CURRENT-DATE values (unless they are executed in extremely close time frames to one another), using those first sixteen characters as the RANDOM seed will guarantee that receiving a duplicate sequence of pseudo-random numbers in two different executions of the program will be highly unlikely.

8.1.72. RANGE

RANGE (number-1 [, number-2]...)

The RANGE function returns a value that is equal to the value of the maximum number-n in the argument list minus the value of the minimum number-n argument.

All number-n arguments are numeric data items and/or numeric literals.

8.1.73. REM

| REI | M Function Syntax |
|----------------------|-------------------|
| REM(number, divisor) | |
| | |

This function returns a numeric value that is the remainder of *number* divided by *divisor*. Both arguments must be numeric data items or numeric literals.

8.1.74. REVERSE

| | REVERSE Function Syntax | |
|-----------------|-------------------------|--|
| REVERSE(string) | | |
| | | |

This function returns the byte-by-byte reversed value of string (a group item, USAGE DISPLAY elementary item or alphanumeric literal).

8.1.75. SECONDS-FROM-FORMATTED-TIME

SECONDS-FROM-FORMATTED-TIME(format, time)

${\bf SECONDS\text{-}FROM\text{-}FORMATTED\text{-}TIME\ Function\ Syntax}$

This function decodes the string time — whose value represents a formatted time — and returns the total number of seconds that string represents.

The time string must contain hours, minutes and seconds. The time argument may be specified as a group item, USAGE DISPLAY elementary item or an alphanumeric literal.

The format argument is a string (a group item, USAGE DISPLAY elementary item or an alphanumeric literal) documenting the format of time using hh, mm and ss to denote where the respective time information can be found. Any other characters found in format represent character positions that will be ignored. For example, a format of hhmmss indicates that time will be treated as a six-digit string value where the first two characters are the number of hours, the next two represent minutes and the last two represent seconds. A format of hh:mm:ss, however, describes time as an eight-character string where characters 3 and 6 will be ignored.

8.1.76. SECONDS-PAST-MIDNIGHT

| | SECONDS-PAST-MIDNIGHT Function Syntax |
|-----------------------|---------------------------------------|
| SECONDS-PAST-MIDNIGHT | |
| | |

This function returns the current time of day expressed as the total number of elapsed seconds since midnight.

8.1.77. SIGN

| | SIGN Function Syntax |
|--------------|----------------------|
| SIGN(number) | |
| | |

The SIGN function returns a -1 if the value of *number* (a numeric literal or numeric data item) is negative, a zero if the value of *number* is exactly zero and a 1 if the value of *number* if greater than 0.

8.1.78. SIN

SIN Function Syntax SIN(angle)

This function determines and returns the trigonometric sine of *angle* (a numeric literal or numeric data item).

The *angle* is assumed to be a value expressed in radians. If you need to determine the sine of an angle measured in degrees, you first need to convert that angle to radians as follows:

COMPUTE radians = (degrees \* FUNCTION PI) / 180

8.1.79. SQRT

SQRT Function Syntax SQRT(number)

The SQRT function returns a numeric value that approximates the square root of *number* (a numeric data item or numeric literal with a non-negative value).

The following two statements produce identical results:

```
01 Result PIC 9(4).9(10).
...
MOVE FUNCTION SQRT(15) TO Result
COMPUTE Result = 15 ^ 0.5
```

8.1.80. STANDARD-DEVIATION

STANDARD-DEVIATION(number-1 [, number-2]...)

This function returns the statistical standard deviation of the list of number-n arguments (numeric data items or numeric literals).

8.1.81. STORED-CHAR-LENGTH

| STORED-CHAR-LENGTH Function Syntax | |
|------------------------------------|--|
| STORED-CHAR-LENGTH(string) | |
| | |

Returns the length — in bytes — of the specified string (a group item, USAGE DISPLAY elementary item or alphanumeric literal), minus the total number of trailing spaces, if any.

8.1.82. SUBSTITUTE

SUBSTITUTE Function Syntax

SUBSTITUTE(string, from-1, to-1 [, from-n, to-n]...)

This function parses *string*, replacing all occurrences of *from-n* strings with the corresponding *to-n* strings.

The from-n strings must match sequences in string exactly with regard to value and case.

A from-n string does not have to be the same length as its corresponding to-n string.

All arguments are group items, USAGE DISPLAY elementary items or alphanumeric literals.

A null to-n string will be treated as a single space.

8.1.83. SUBSTITUTE-CASE

SUBSTITUTE-CASE Function Syntax SUBSTITUTE-CASE(string, from-1, to-1 [, from-n, to-n]...)

The SUBSTITUTE-CASE function operates the same as the SUBSTITUTE (see [SUBSTITUTE], page 448) function, except that *from-n* string matching is performed without regard to case.


All arguments are group items, USAGE DISPLAY elementary items or alphanumeric literals.

8.1.84. SUM

SUM Function Syntax SUM(number-1 [, number-2]...)

The SUM function returns a value that is the sum of number-n arguments (these may be numeric data items or numeric literals).

8.1.85. TAN



This function determines and returns the trigonometric tangent of angle (a numeric literal or numeric data item).

The angle is assumed to be a value expressed in radians. If you need to determine the tangent of an angle measured in degrees, you first need to convert that angle to radians as follows:

COMPUTE radians = (degrees \* FUNCTION PI) / 180

8.1.86. TEST-DATE-YYYYMMDD

${\bf TEST\text{-}DATE\text{-}YYYYMMDD\ Function\ Syntax}$

TEST-DATE-YYYYMMDD(date)

This function determines if the supplied date argument (a numeric integer data item or literal) is a valid date.

A valid date is one of the form yyyymmdd in the range 1601/01/01 to 9999/12/31, with no more than the expected maximum number of days in the month, accounting for leap year.

If the *date* is valid, a 0 value is returned. If it isn't, a value of 1, 2 or 3 is returned signalling the problem lies with the year, month or day, respectively.

8.1.87. TEST-DAY-YYYYDDD

TEST-DAY-YYYYDDD Function Syntax

TEST-DATE-YYYYDDD(date)

This function determines if the supplied date (a numeric integer data item or literal) is a valid

A valid date is one of the form yyyyddd in the range 1601001 to 9999365. Leap year is accounted for in determining the maximum number of days in a year.

If the date is valid, a 0 value is returned. If it isn't, a value of 1 or 2 is returned signalling the problem lies with the year or day, respectively.

8.1.88. TEST-FORMATTED-DATETIME

TEST-FORMATTED-DATETIME Function Syntax

TEST-FORMATTED-DATETIME (argument-1, argument-2)

TEST-FORMATTED-DATETIME tests whether a date literal representing a date, a time or a combined date and time is valid according to the specified format.

argument-1 shall be a national or alphanumeric literal. The content must be either a date format or a combined date and time format.

argument-2 must be a data item of the same type as argument-1.

Returned value:

If no format or range problems occur during evaluation of argument-2 according to the format in argument-1, the returned value is zero. Otherwise the returned value is the ordinal character position at which the first error in argument-2 was detected.

8.1.89. TEST-NUMVAL

| | TEST-NUMVAL Function Syntax |
|---------------------|-----------------------------|
| TEST-NUMVAL(string) | |
| | |

The TEST-NUMVAL function evaluates string (a group item, USAGE DISPLAY elementary item or alphanumeric literal) for being appropriate for use as the string argument to a NUMVAL (see [NUMVAL], page 427) function, returning to a integer a zero value if it is appropriate otherwise if one or more characters are in error, the position of the first character in error or the length of the field plus one for other cases such as all spaces.

Note that these errors include but are not limited to: argument (*string*) is zero length, contains only spaces or contains valid characters but is incomplete, such as the string '+.'.

8.1.90. TEST-NUMVAL-C

TEST-NUMVAL-C Function Syntax

TEST-NUMVAL-C(string[,symbol])

This function evaluates *string* (a group item, USAGE DISPLAY elementary item or alphanumeric literal) for being appropriate for use as the *string* argument to a NUMVAL-C (see [NUMVAL-C], page 428) function, returning to a integer a zero value if it is appropriate otherwise if one or more characters are in error, the position of the first character in error or the length of the field plus one for other cases such as all spaces.

Note that these errors include but are not limited to: argument (*string*) is zero length, contains only spaces or contains valid characters but is incomplete, such as the string '+.'.

The optional *symbol* argument serves the same function — and has the same default and possible values — as the corresponding argument of the NUMVAL-C function.

8.1.91. TEST-NUMVAL-F

TEST-NUMVAL-F(string)

This function evaluates *string* (a group item, USAGE DISPLAY elementary item or alphanumeric literal) for being appropriate for use as the *string* argument to a NUMVAL-F (see [NUMVAL-F], page 430) function, returning to a integer a zero value if it is appropriate otherwise if one or more characters are in error, the position of the first character in error or the length of the field plus one for other cases such as all spaces.

Note that these errors include but are not limited to: argument (string) is zero length, contains only spaces or contains valid characters but is incomplete, such as the string '+.'.

8.1.92. TRIM

TRIM Function Syntax TRIM(string [, LEADING|TRAILING])

This function removes LEADING or TRAILING spaces from string (a group item, USAGE DISPLAY elementary item or alphanumeric literal).

The second argument is specified as a keyword, not a quoted string or identifier. If no second argument is specified, *both* leading and trailing spaces will be removed. The case (upper, lower or mixed) of this argument is irrelevant.

8.1.93. UPPER-CASE

| | UPPER-CASE Function Syntax |
|--------------------|----------------------------|
| UPPER-CASE(string) | |

This function returns the value of *string* (a group item, USAGE DISPLAY elementary item or alphanumeric literal), converted entirely to upper case.

What constitutes a "letter" (or upper/lower case too, for that manner) may be influenced through the use of a CHARACTER CLASSIFICATION (see [OBJECT-COMPUTER], page 82).

8.1.94. VARIANCE

VARIANCE Function Syntax VARIANCE(number-1 [, number-2]...)

This function returns the statistical variance of the specified list of *number-n* arguments (these may be numeric data items or numeric literals).

8.1.95. WHEN-COMPILED

WHEN-COMPILED Function Syntax WHEN-COMPILED

The WHEN-COMPILED intrinsic function, not to be confused with the WHEN-COMPILED (see [Special Registers], page 227) special register, returns the date and time the program was compiled, in ASCII.

Since this function has no arguments, no parenthesis should be specified.

Unlike the WHEN-COMPILED special register, which has an ASCII value of the compilation date/time in the format mm/dd/yyhh.mm.ss, the WHEN-COMPILED intrinsic function returns the compilation date/time as an ASCII string in the format yyyymmddhhmmssnnoooo, where yyyymmdd is the date, hhmmss is the time, nn is the hundredths of a second component of the compilation time, if available (or 00 if it isn't) and ooooo is the time zone offset from GMT.

If the -fintrinsics=WHEN-COMPILED switch or -fintrinsics=ALL switch is specified to the compiler or the REPOSITORY (see [REPOSITORY], page 93) paragraph specifies either FUNCTION WHEN-COMPILED INTRINSIC or FUNCTION ALL INTRINSIC, then references to WHEN-COMPILED (without a leading FUNCTION keyword will always reference this intrinsic function and there will be no way to access the WHEN-COMPILED special register.

8.1.96. YEAR-TO-YYYY

YEAR-TO-YYYY Function Syntax

YEAR-TO-YYYY(yy [, yy-cutoff [, yy-execution-time]])

YEAR-TO-YYYY converts yy — a two-digit year — to a four-digit format (yyyy).

The optional yy-cutoff argument is the year cutoff used to delineate centuries; if yy meets or exceeds this cutoff value, the result will be 19yy; if yy is less than the cutoff, the result will be 20yy. The default cutoff value if no second argument is given will be 50.

The optional yy-execution-time argument (a numeric integer data item or literal) The default execution time value if no third argument is given will be now equivalent to specifying (FUNCTION NUMVAL (FUNCTION CURRENT-DATE (1:4))).

All arguments must be numeric data items or numeric literals.

8.1.97. BOOLEAN-OF-INTEGER

BOOLEAN-OF-INTEGER Function Syntax

BOOLEAN-OF-INTEGER(argument-1 argument-2)

This option is not yet implemented.

The included file NEWS will indicate when it is.

BOOLEAN-OF-INTEGER returns a boolean item of usage bit representing the binary value of argument-1. argument-2 specifies the length of the boolean data item that is returned.

argument-1 must be a positive integer.

argument-2 must be a positive non-zero integer

Returned value is a boolean item of usage bit that has the same bit configuration as the binary representation of the value of *argument-1*, where the rightmost boolean position is the low-order binary digit. The boolean value is zero-filled or truncated on the left, if necessary, in order to return a boolean item whose length is specified by *argument-2* in therms of boolean positions.

8.1.98. CHAR-NATIONAL

CHAR-NATIONAL Function Syntax

CHAR-NATIONAL(argument-1)

This option is not yet implemented.

The included file NEWS will indicate when it is.

CHAR-NATIONAL returns a one character value that is a character in the national program collating sequence having the ordinal position equal to the value of the argument.

argument-1 must be a integer and greater than zero and less than or equal to the number of positions in the national program collating sequence.

8.1.99. DISPLAY-OF

DISPLAY-OF Function Syntax

DISPLAY-OF(argument-1 [argument-2])

This option is not yet implemented.

The included file NEWS will indicate when it is.

DISPLAY-OF returns a character string containing the alphabetic coded character set representation of the national characters in the argument.

argument-1 must be of class national.

argument-2 must be a of class alphabetic or alphanumeric and is one character position in length. It specifies an alphanumeric substitution character for use in conversion of national characters for which there is no corresponding alphanumeric character.

A character string is returned with each national character of argument-1 converted to its corresponding alphanumeric character representation, if any.

If argument-2 is specified, the alphanumeric substitution character is returned for each national character in argument-1 that has no corresponding alphanumeric character representation.

If argument-2 is un-specified, and argument-1 contains a national character for which there is no corresponding alphanumeric character representation, an substitution character is used as the corresponding alphanumeric character and the EC-DATA-CONVERSION exception condition is set.

The length of the returned value is the number of character positions of usage display required to hold the converted argument and depends on the number of characters contained in *argument-1*.

8.1.100. EXCEPTION-FILE-N

EXCEPTION-FILE-N Function Syntax

EXCEPTION-FILE-N

This option is not yet implemented.

The included file NEWS will indicate when it is.

EXCEPTION-FILE-N returns a national character string that is the I/O status value and filename of the file connector, if any, associated with the last exception status.

The value returned has a length that is based on its contents and the concents are as follows:

If the last exception status is not an EC-I-O exception condition, the returned value is two national zeros.

The returned value is two national spaces when the last exception status indicates an EC-I-O exception condition that originates from one of the following statements:

- a RAISE statement.
- an EXIT or a GOBACK statement with a RAISING phrase that specifies an EC-I-O exception-name.

Otherwise the returned value is a character string that is as long as is needed to contain the I-O status value and the filename. The first two characters are the I-O status value in national characters. The succeeding characters contain the file-name exactly as specified in the SELECT clause converted at runtime to the runtime national character set.

The documentation of the CBL\_ERROR\_PROC built-in system subroutine (see [CBL\_ERROR\_PROC], page 501) built-in subroutine illustrates the use of this function.

8.1.101. EXCEPTION-LOCATION-N

EXCEPTION-LOCATION-N Function Syntax

EXCEPTION-LOCATION-N

This option is not yet implemented.

The included file NEWS will indicate when it is.

EXCEPTION-LOCATION-N returns an national character string containing exception information from the most-recently failing statement. The information is returned to a 1023 character string in one of the following formats, depending on the nature of the failure:

- primary-entry-point-name; paragraph OF section; statement-number
- primary-entry-point-name; section; statement-number
- primary-entry-point-name; paragraph; statement-number
- primary-entry-point-name; statement-number

Since this function has no arguments, no parenthesis should be specified.

The program must be compiled with the <code>-debug</code> switch, <code>-ftraceall</code> switch or <code>-g</code> switch for this function to return any meaningful information.

The documentation of the CBL\_ERROR\_PROC built-in system subroutine (see [CBL\_ERROR\_PROC], page 501) built-in subroutine illustrates the use of this function.

8.1.102. INTEGER-OF-BOOLEAN

INTEGER-OF-BOOLEAN Function Syntax

INTEGER-OF-BOOLEAN(argument-1)

This option is not yet implemented.

The included file NEWS will indicate when it is.

INTEGER-OF-BOOLEAN returns the numeric value of the boolean string in argument-1 which is class boolean.

Returned value as argument-1 is assigned to a temporary boolean data item of usage bit described with the same number of boolean positions.

The unsigned binary value represented by the same bit configuration as the bit configuration of that temporary boolean data item is determined.

Note: Binary representation is a mathematical concept. It is not required that this representation be the same as a COBOL representation.

8.1.103. NATIONAL-OF

NATIONAL-OF Function Syntax

NATIONAL-OF(argument-1 [argument-2])

This option is not yet implemented.

The included file NEWS will indicate when it is.

NATIONAL-OF returns a character string containing the national character representation of the characters in the argument which must be of class boolean.

A character string is returned with each alphanumeric character in *argument-1* converted to its corresponding national coded character set representation.

If argument-2 is specified, each character in argument-1 that has no corresponding national representation is converted to the substitution character specified by argument-2.

If argument-2 is unspecified and argument-1 contains an alphanumeric character for which there is no corresponding national character representation, a substitution character is used as the corresponding national character and the EC-DATA-CONVERSION exception condition is set to exist.

The length of the returned value is the number of character positions of usage national required to hold the converted argument and depends on the number of characters contained in argument-1.

8.1.104. STANDARD-COMPARE

STANDARD-COMPARE Function Syntax

STANDARD-COMPARE(argument-1 argument-2 [ordering-name-1] [argument-4])

This option is not yet implemented.

The included file NEWS will indicate when it is.

STANDARD-COMPARE returns a character indicating the result of comparing argument-1 as a alphanumeric and argument-2 using a cultural ordering table.

- 1. argument-1 shall be of class alphabetic, alphanumeric, or national.
- 2. argument-2 shall be of class alphabetic, alphanumeric, or national.
- 3. argument-1 and argument-2 may be of different classes.
- 4. Neither argument-1 nor argument-2 shall be a zero-length literal.
- 5. ordering-name-1, if specified, shall be associated with a cultural ordering table in the ORDER TABLE clause of the SPECIAL-NAMES paragraph. ordering-name-1 identifies the ordering table to be used for the comparison. If ordering-name-1 is not specified, the default ordering table 'ISO14651\_2010\_TABLE1' described in Appendix A of ISO/IEC 14651:2011 shall be used.
- 6. argument-4, if specified, shall be a positive nonzero integer.

Returned values:

- 1. If argument-4 is unspecified, the highest level defined in the ordering table is used for the comparison.
- 2. If the cultural ordering table is not available on the processor, or the specified ordering level is not available, or the level number specified by *argument-4* is not defined in the ordering table, the EC-ORDER-NOT-SUPPORTED exception condition is set.
- 3. If the arguments are of different classes, and one is national, the other argument is converted to class national for purposes of comparison.
- 4. For purposes of comparison, trailing spaces are truncated from the operands except that an operand consisting of all spaces is truncated to a single space.
- 5. argument-1 and argument-2 are compared in accordance with the ordering table and ordering level being used.

Note: This comparison is culturally sensitive and the default ordering table is acceptable for most cultures. It is not necessarily a character-by-character comparison and not necessarily a case-sensitive comparison. In order to use this function, users should understand the types of comparisons specified by ISO/IEC 14651:2D11 and the ordering tables in use for their installation.

- 6. The returned value is:
 - '=' the arguments compare equal,
 - '-=.:' argument-1 is less than argument-2,
 - ':>' argument-1 is greater than argument-2.
- 7. The length of the returned value is 1.

8.1.105. BIT-OF

BIT-OF Function Syntax BIT-OF(argument-1)

BIT-OF function returns an alphanumeric character string of '1' and '0' characters, which represents the binary value of each byte in the argument used on input.

- 1. The function type is alphanumeric.
- 2. argument-1 must be a data item, literal, or an intrinsic function result of any data class.

- 1. An alphanumeric character string consisting of the binary representation of each byte in argument-1.
- 2. The length of the character string returned, in bytes, is eight times the length of argument-1, in bytes.

8.1.106. BIT-TO-CHAR

${\bf BIT\text{-}TO\text{-}CHAR}\ \ {\bf Function}\ \ {\bf Syntax}$


BIT-TO-CHAR{argument-1)

BIT-TO-CHAR function returns a character string that represents a bit pattern supplied on input.

- 1. The function type is alphanumeric.
- 2. argument-1 must be an alphanumeric literal, alphanumeric data item, or alphanumeric group item.
- 3. argument-1 must consist only of the characters '0' and '1'.
- 4. The length of argument-1 must be a multiple of 8 bytes.

- 1. A character string consisting of bytes representing the sequence of '0' and '1' characters in argument-1.
- 2. The length of the result string is equal to the length of the input string divided by 8.

8.1.107. HEX-OF



HEX-OF function returns an alphanumeric character string consisting of a hexadecimal representation of the argument used on input.

- 1. The type of the function is alphanumeric.
- 2. argument-1 must be a data item, literal, or an intrinsic function result of any data class.

- 1. An alphanumeric character string consisting of a hexadecimal representation of argument-1.
- 2. The length of the character string returned, in bytes, is twice the length of argument-1, in bytes.

8.1.108. HEX-TO-CHAR

HEX-TO-CHAR Function Syntax

HEX-TO-CHAR{argument-1)

HEX-TO-CHAR function returns a character string that represents the hexadecimal digit characters supplied on input.

- 1. The type of the function is alphanumeric.
- 2. argument-1 must be an alphanumeric literal, alphanumeric data item, or alphanumeric group item.
- 3. argument-1 must consist only of the characters '0' through '9', 'A' through 'F', and 'a' through 'f'.
- 4. The length of argument-1 must be a multiple of 2 bytes.

- 1. A character string of bytes representing the hexadecimal digit characters of argument-1.
- 2. The length of the result string is equal to the length of the input string divided by 2.

8.2. Built-In System Subroutines

There are a number of built-in system subroutines included with GnuCOBOL.

Generally, these routines are intended to match those available in Micro Focus COBOL, ACUCOBOL and directly for GnuCOBOL.

It is recommended to change the CBL\_OC routines to CBL\_GC for forward compatibility as at some point they will be removed as they are a hangover from Open Cobol.

Prefix explanation:

C\$ \rightarrow ACU \rightarrow MF

CBL\_GC\_ (For backwards compatibility some routines are also available as CBL\_OC\_ as well): but these wonderful extensions are *only* available with GnuCOBOL.

These routines, all executed via their *upper-case names* via the CALL statement (see [CALL], page 253), are capable of performing the following functions:

- Changing the current directory
- Copying files
- Creating a directory
- Creating, Opening, Closing, Reading and Writing byte-stream files
- Deleting directories (folders)
- Deleting files
- Determining how many arguments were passed to a subroutine
- Getting file information (size and last-modification date/time)
- Getting the length (in bytes) of an argument passed to a subroutine
- Justifying a field left-, right- or center-aligned
- Moving files (a destructive "copy")
- Putting the program "to sleep", specifying the sleep time in seconds
- Putting the program "to sleep", specifying the sleep time in nanoseconds; Caveat: although you'll express the time in nanoseconds, Windows systems will only be able to sleep at a millisecond granularity
- Retrieving information about the currently-executing program
- Submitting a command to the shell environment appropriate for the version of GnuCOBOL you are using for execution

Early versions of Micro Focus COBOL allowed programmers to access various runtime library routines by using a single two-digit hexadecimal number as the entry-point name. These were known as call-by-number routines. Over time, Micro Focus COBOL evolved, replacing most of the call-by-number routines with ones accessible using a more conventional call-by-name technique.

Most of the call-by-number routines have evolved into even more powerful call-by-name routines, many of which are supported by GnuCOBOL.

Some of the original call-by-number routines never evolved call-by-name equivalents; Gnu-COBOL supports some of these routines.

The following sections describe the various built-in subroutines. All subroutine arguments are mandatory except where explicitly noted to the contrary. Any subroutine returning a value to the RETURN-CODE special register (see [Special Registers], page 227) could utilize the RETURNING clause on the CALL statement to return the result back to the full-word binary data item of your choice.

8.2.1. C\$CALLEDBY

C\$CALLEDBY Built-In Subroutine Syntax

CALL "C\$CALLEDBY" USING prog-name-area

This routine returns the name of the program that called the currently-executing program. The program name will be returned, left-justified and space filled, in *prog-name-area* argument, which should be a PIC X elementary item or a group item. If *prog-name-area* is too small to receive the entire program name, the program name value will be truncated (on the right) to fit.

The RETURN-CODE special register (see [Special Registers], page 227) will be set to one of the following values:

- -1 An error occurred. The *prog-name-area* contents will be unchanged.
- The program calling C\$CALLEDBY was not called by any other program (in other words, it is a main program). The *prog-name-area* contents will be set entirely to spaces.
- The program calling C\$CALLEDBY was indeed called by another program, and that program's name has been saved in *prog-name-area*.

8.2.2. C\$CHDIR

C\$CHDIR Built-In Subroutine Syntax

CALL "C\$CHDIR" USING directory-path, result

This routine makes directory-path (an alphanumeric literal or identifier) the current directory.

The return code of the operation is returned both in the *result* argument (any non-edited numeric identifier) as well as in the RETURN-CODE special register (see [Special Registers], page 227). The return code of the operation will be either 0=Success or 128=failure.

The directory change remains in effect until the program terminates (in which the original current directory at the time the program was started will be automatically restored) or until another C\$CHDIR or a CBL\_CHANGE\_DIR built-in system subroutine (see [CBL\_CHANGE\_DIR], page 492) is executed.

8.2.3. C\$COPY

C\$COPY Built-In Subroutine Syntax

CALL "C\$COPY" USING src-file-path, dest-file-path, 0

Use this subroutine to copy file src-file-path to dest-file-path as if it were done via the cp (Unix/OSX) or COPY (Windows) command.

Both file path arguments may be alphanumeric literals or identifiers.

The third argument is required, but is unused.

If the attempt to copy the file fails (for example, it or the destination directory doesn't exist), the RETURN-CODE special register (see [Special Registers], page 227) will be set to 128; on successful completion it will be set to 0.

8.2.4. C\$DELETE

C\$DELETE Built-In Subroutine Syntax

CALL "C\$DELETE" USING file-path, 0

This routine deletes the file specified by the *file-path* argument (an alphanumeric literal or identifier) just as if that were done using the rm (Unix/OSX) or ERASE (Windows) command.

The second argument is required, but is unused.

If the attempt to delete the file fails (for example, it doesn't exist), the RETURN-CODE special register (see [Special Registers], page 227) will be set to 128; on successful completion it will be set to 0.

8.2.5. C\$FILEINFO

C\$FILEINFO Built-In Subroutine Syntax

```
CALL "C$FILEINFO" USING file-path, file-info
```

With this routine you may retrieve the size of the file specified as the *file-path* argument (an alphanumeric literal or identifier) and the date/time that file was last modified. File size information may not be available in the particular GnuCOBOL build / Operating System combination you are using and may therefore always be returned as zero. The information is returned to the *file-info* argument, which is defined as the following 16-byte area:

01 File-Info.

05 File-Size-In-Bytes PIC 9(18) COMP.

05 Mod-YYYYMMDD PIC 9(8) COMP. \*> Modification Date 05 Mod-HHMMSS00 PIC 9(8) COMP. \*> Modification Time

The last two decimal digits in the modification time will always be 00.

If the subroutine is successful, a value of 0 will be returned in the RETURN-CODE special register (see [Special Registers], page 227). Failure to retrieve the needed statistics on the file will cause a RETURN-CODE special register value of 35 to be passed back. Supplying less than two arguments will generate a 128 RETURN-CODE special register value.

8.2.6. C\$GETPID

C\$GETPID Built-In Subroutine Syntax CALL "C\$GETPID"

Use this subroutine to return the PID (process ID) of the executing GnuCOBOL program. The PID value is returned into the RETURN-CODE special register (see [Special Registers], page 227). There are no arguments to this routine.

8.2.7. C\$JUSTIFY

C\$JUSTIFY Built-In Subroutine Syntax

CALL "C\$JUSTIFY" USING data-item, "justification-type"

Use C\$JUSTIFY to left, right or center-justify an alphabetic, alphanumeric or numeric edited data-item. The optional *justification-type* argument indicates the type of the justification to be performed. Its value is interpreted as follows:

'C' the value will be centered

'R' the value will be right-justified, space-filled to the left

'L' the value will be left-justified, space-filled to the right

If it begins with anything else, or is absent, it will be treated as if it is present and begins with a capital 'R'

8.2.8. C\$MAKEDIR

C\$MAKEDIR Built-In Subroutine Syntax

CALL "C\$MAKEDIR" USING dir-path

With this routine you may create a new directory — the name of which is supplied as the dir-path argument (an alphanumeric literal or identifier).

Only the lowest-level directory (last) in the specified path can be created — all others must already exist. This subroutine will *not* behave as a mkdir -p (Unix) or mkdir /p (Windows).

The RETURN-CODE special register (see [Special Registers], page 227) will be set to the return code of the operation; the value will be either 0=Success or 128=failure.

8.2.9. C\$NARG

C\$NARG Built-In Subroutine Syntax CALL "C\$NARG" USING arg-count-result

This subroutine returns the number of arguments passed to the program that calls it back to in the numeric field arg-count-result. When called from within a user-defined function, a value of one (1) is returned if any arguments were passed to the function or a zero (0) otherwise.

When called from a main program, the returned value will always be 0.

8.2.10. C\$PARAMSIZE

C\$PARAMSIZE Built-In Subroutine Syntax

CALL "C\$PARAMSIZE" USING argument-number

This subroutine returns the size (in bytes) of the subroutine argument supplied using the argument-number parameter (a numeric literal or data item).

The size is returned in the RETURN-CODE special register (see [Special Registers], page 227).

If the specified argument does not exist, or an invalid argument number is specified, a value of 0 is returned.

8.2.11. C\$PRINTABLE

C\$PRINTABLE Built-In Subroutine Syntax CALL "C\$PRINTABLE" USING data-item [, char]

The C\$PRINTABLE subroutine converts the contents of the data-item specified as the first argument to printable characters. Those characters that are deemed printable (as defined by the character set used by data-item) will remain unchanged, while those that are NOT printable will be converted to the character specified as the second argument.

If no *char* argument is provided, a period ('.') will be used.

 $\it Note$: CBL\_GC\_PRINTABLE replaces this although it is currently still supported for legacy reasons.

8.2.12. C\$SLEEP

C\$SLEEP Built-In Subroutine Syntax

CALL "C\$SLEEP" USING seconds-to-sleep

C\$SLEEP puts the program to sleep for the specified number of seconds and/or fractions of a second. The seconds-to-sleep argument may be a numeric literal or data item.

Sleep times less than 1 will be interpreted as 0, subject to the speed of the CPU and the O/S (Operating System) used, as well as the timing of the generated C code, which can immediately returns control to the calling program without any sleep delay.

When using a variable argument defined as 9(n)v9(m) where n is maximum seconds in 7 days, i.e., $(60 \times 60 \times 24 \times 7) = 604,800$ (seconds) and m is at a point too fast for the CPU and O/S. In practice m should be 2 for a hundredth of a second but actual testing against the target CPU would be need.

The maximum time can be adjusted by the define MAX\_SLEEP\_TIME during compilation of the compiler [and no I do not know where it is in the codebase] e.g.:

/\* maximum sleep time in seconds, currently 7 days \*/
#define MAX\_SLEEP\_TIME 3600\*24\*7

8.2.13. C\$TOLOWER

C\$TOLOWER Built-In Subroutine Syntax

CALL "C\$TOLOWER" USING data-item, BY VALUE convert-length

This routine will converts the *convert-length* (a numeric literal or data item) leading characters of *data-item* (an alphanumeric identifier) to lower-case.

The convert-length argument must be specified BY VALUE (see [CALL], page 253). Any characters in data-item after the convert-length point will remain unchanged.

If convert-length is negative or zero, no conversion will be performed.

8.2.14. C\$TOUPPER

C\$TOUPPER Built-In Subroutine Syntax

CALL "C\$TOUPPER" USING data-item, BY VALUE convert-length

This routine will converts the *convert-length* (a numeric literal or data item) leading characters of *data-item* (an alphanumeric identifier) to upper-case.

The convert-length argument must be specified BY VALUE (see [CALL], page 253). Any characters in data-item after the convert-length point will remain unchanged.

If convert-length is negative or zero, no conversion will be performed.

8.2.15. CBL\_AND

CBL\_AND Built-In Subroutine Syntax

CALL "CBL\_AND" USING item-1, item-2, BY VALUE byte-length

| Old
Arg 1
Bit
===== | 01d
Arg 2
Bit
===== | New Arg 2 Bit ===== | This subroutine performs a bit-by-bit logical AND operation between the left-most 8*byte-length corresponding bits of item-1 and item-2, storing the resulting bit string into item-2. The truth table shown to the left documents the AND process. |
|------------------------------|------------------------------|---------------------|---|
| 0 | 0 | 0 | |
| 0 | 1 | 0 | The item-1 argument may be an alphanumeric literal or a data |
| 1 | 0 | 0 | item and item-2 must be a data item. The length of both item-1 |
| 1 | 1 | 1 | and item-2 must be at least 8*byte-length. |
| | | | |

The byte-length argument may be a numeric literal or data item, and must be specified using BY VALUE (see [CALL], page 253).

Any bits in item-2 after the 8\*byte-length point will be unaffected.

8.2.16. CBL\_CHANGE\_DIR

CBL\_CHANGE\_DIR Built-In Subroutine Syntax

CALL "CBL\_CHANGE\_DIR" USING directory-path

This routine makes directory-path (an alphanumeric literal or identifier) the current directory.

The return code of the operation, which will be either 0=Success or 128=failure, is returned in the RETURN-CODE special register (see [Special Registers], page 227).

The directory change remains in effect until the program terminates (in which the original current directory at the time the program was started will be automatically restored) or until another CBL\_CHANGE\_DIR or a C\$CHDIR built-in system subroutine (see [C\$CHDIR], page 478) is executed.

8.2.17. CBL\_CHECK\_FILE\_EXIST

CBL\_CHECK\_FILE\_EXIST Built-In Subroutine Syntax

```
CALL "CBL_CHECK_FILE_EXIST" USING file-path, file-info
```

With this routine you may retrieve the size of the file specified as the *file-path* argument (an alphanumeric literal or identifier) and the date/time that file was last modified. File size information may not be available in the particular GnuCOBOL build / Operating System combination you are using and may therefore always be returned as zero.

The information is returned to the *file-info* argument, which is defined as the following 16-byte area:

```
01
   file-info.
    05 File-Size-In-Bytes
                           PIC 9(18)
                                        COMP.
    05 Mod-DD
                            PIC 9(2)
                                        COMP.
                                               *> Modification Date
    05 Mod-MO
                            PIC 9(2)
                                        COMP.
    05 Mod-YYYY
                            PIC 9(4)
                                        COMP.
    05 Mod-HH
                            PIC 9(2)
                                        COMP.
                                               *> Modification Time
    05 Mod-MM
                            PIC 9(2)
                                        COMP.
    05 Mod-SS
                            PIC 9(2)
                                        COMP.
    05 FILLER
                            PIC 9(2)
                                        COMP.
                                               *> Always 00
```

If the subroutine is successful, a value of 0 will be returned in the RETURN-CODE special register (see [Special Registers], page 227). Failure to retrieve the needed statistics on the file will cause a RETURN-CODE special register value of 35 to be passed back. Supplying less than two arguments will generate a 128 RETURN-CODE special register value.

8.2.18. CBL\_CLOSE\_FILE

CBL\_CLOSE\_FILE Built-In Subroutine Syntax

CALL "CBL\_CLOSE\_FILE" USING file-handle

The CBL\_CLOSE\_FILE subroutine closes a byte stream file previously opened by either the CBL\_

The CBL\_CLOSE\_FILE subroutine closes a byte stream file previously opened by either the CBL\_OPEN\_FILE built-in system subroutine (see [CBL\_OPEN\_FILE], page 523) or CBL\_CREATE\_FILE built-in system subroutine (see [CBL\_CREATE\_FILE], page 497) subroutines.

If the file defined by the *file-handle* argument (a PIC X(4) USAGE COMP-X data item) was opened for output, an implicit CBL\_FLUSH\_FILE built-in system subroutine (see [CBL\_FLUSH\_FILE], page 505) will be performed before the file is closed.

If the subroutine is successful, a value of 0 will be returned in the RETURN-CODE special register (see [Special Registers], page 227). Failure will cause a RETURN-CODE special register value of -1 to be passed back.

8.2.19. CBL\_COPY\_FILE

CBL\_COPY\_FILE Built-In Subroutine Syntax

CALL "CBL\_COPY\_FILE" USING src-file-path, dest-file-path

Use this subroutine to copy file *src-file-path* to *dest-file-path* as if it were done via the cp (Unix/OSX) or COPY (Windows) command.

Both arguments may be alphanumeric literals or identifiers.

If the attempt to copy the file fails (for example, it or the destination directory doesn't exist), the RETURN-CODE special register (see [Special Registers], page 227) will be set to 128; on successful completion it will be set to 0.

8.2.20. CBL\_CREATE\_DIR

CBL\_CREATE\_DIR Built-In Subroutine Syntax

CALL "CBL\_CREATE\_DIR" USING dir-path

With this routine you may create a new directory — the name of which is supplied as the dir-path argument (an alphanumeric literal or identifier).

Only the lowest-level directory (last) in the specified path can be created — all others must already exist. This subroutine will *not* behave as a mkdir -p (Unix) or mkdir /p (Windows).

The RETURN-CODE special register (see [Special Registers], page 227) will be set to the return code of the operation; the value will be either 0=Success or 128=failure.

8.2.21. CBL\_CREATE\_FILE

CBL\_CREATE\_FILE Built-In Subroutine Syntax

CALL "CBL\_CREATE\_FILE" USING file-path, 2, 0, 0, file-handle

The CBL\_CREATE\_FILE subroutine creates the new file specified using the file-path argument and opens it for output as a byte-stream file usable by CBL\_WRITE\_FILE built-in system subroutine (see [CBL\_WRITE\_FILE], page 530).

Arguments 2, 3 and 4 should be coded as the constant values shown. CBL\_CREATE\_FILE is actually a special-case of the CBL\_OPEN\_FILE built-in system subroutine (see [CBL\_OPEN\_FILE], page 523) routine — see that routine for a description of the meanings of arguments 2, 3 and 4.

A file-handle (PIC X(4) USAGE COMP-X) will be returned, for use on any subsequent CBL\_WRITE\_FILE built-in system subroutine (see [CBL\_WRITE\_FILE], page 530) or CBL\_CLOSE\_FILE built-in system subroutine (see [CBL\_CLOSE\_FILE], page 494) calls.

The success or failure of the subroutine will be reported back in the RETURN-CODE special register (see [Special Registers], page 227), with a value of -1 indicating an invalid argument and a value of 0 indicating success.

8.2.22. CBL\_DELETE\_DIR

CBL\_DELETE\_DIR Built-In Subroutine Syntax

CALL "CBL\_DELETE\_DIR" USING dir-path

This subroutine deletes an empty directory.

The only argument — dir-path (an alphanumeric literal or identifier) — is the name of the directory to be deleted.

Only the lowest-level directory (last) in the specified path will be deleted, and that directory must be empty to be deleted.

The RETURN-CODE special register (see [Special Registers], page 227) will be set to the return code of the operation; the value will be either 0=Success or 128=failure.

8.2.23. CBL\_DELETE\_FILE

$CBL\_DELETE\_FILE\ Built-In\ Subroutine\ Syntax$

CALL "CBL\_DELETE\_FILE" USING file-path

This routine deletes the file specified by the *file-path* argument (an alphanumeric literal or identifier) just as if that were done using the rm (Unix/OSX) or ERASE (Windows) command.

If the attempt to delete the file fails (for example, it doesn't exist), the RETURN-CODE special register (see [Special Registers], page 227) will be set to 128; on successful completion it will be set to 0.

8.2.24. CBL\_EQ

$CBL_{-}EQ$ Built-In Subroutine Syntax

CALL "CBL\_EQ" USING item-1, item-2, BY VALUE byte-length

| Old
Arg 1
Bit
===== | 01d
Arg 2
Bit
===== | New Arg 2 Bit ===== | This subroutine performs a bit-by-bit comparison between the left-most 8*byte-length corresponding bits of item-1 and item-2, storing the resulting bit string into item-2. The truth table shown to the left documents the EQ process. |
|------------------------------|------------------------------|---------------------|---|
| 0 | 0 | 1 | |
| 0 | 1 | 0 | The item-1 argument may be an alphanumeric literal or a data |
| 1 | 0 | 0 | item and item-2 must be a data item. The length of both item-1 |
| 1 | 1 | 1 | and item-2 must be at least 8*byte-length. |

The *byte-length* argument may be a numeric literal or data item, and must be specified using BY VALUE (see [CALL], page 253).

Any bits in item-2 after the 8\*byte-length point will be unaffected.

8.2.25. CBL\_ERROR\_PROC

CBL\_ERROR\_PROC Built-In Subroutine Syntax

CALL "CBL\_ERROR\_PROC" USING function, program-pointer

This routine registers a general error-handling routine.

The function argument must be a numeric literal or a 32-bit binary data item (USAGE BINARY-LONG, for example) with a value of 0 or 1. A value of 0 means that you will be registering ("installing") an error procedure while a value of 1 indicates you're de-registering ("uninstalling") a previously-installed error procedure.

The program-pointer must be a data item with a USAGE (see [USAGE], page 198) of PROGRAM-POINTER containing the address of your error procedure. This item should be given a value using the SET Program-Pointer statement (see [SET Program-Pointer], page 331). If the error procedure is written in GnuCOBOL, it must be a subroutine, not a user-defined function.

A success (0) or failure (non-0) result will be passed back in the RETURN-CODE special register (see [Special Registers], page 227).

A custom error procedure will trigger when a runtime error condition is encountered. An error procedure may be registered by a main program or a subprogram, but regardless of from where it was registered, it applies to the overall program compilation group and will trigger when a runtime error occurs anywhere in the executable program. If the error procedure was defined by a subprogram, that program must be loaded at the time the error procedure is executed.

An error procedure may be used to take whatever actions might be warranted to display additional information or to gracefully close down work in progress, but it cannot *prevent* the termination of program execution; should the error procedure not issue its own STOP RUN, control will return back to the standard error routine when the error procedure exits.

The code within the handler will be executed and — once the handler issues a return, if it was written in C, or an EXIT PROGRAM statement (see [EXIT], page 282) or GOBACK statement, if it was written in GnuCOBOL, the system-standard error handling routine will be executed.

Only one user-defined error procedure may be in effect at any time.

The following is a sample GnuCOBOL program that registers an error procedure. The output of that program is shown as well. As as you can see, the error handler's messages appear followed by the standard GnuCOBOL message.

- 1. IDENTIFICATION DIVISION.
- 2. PROGRAM-ID. DemoERRPROC.
- 3. ENVIRONMENT DIVISION.
- 4. DATA DIVISION.
- 5. WORKING-STORAGE SECTION.
- 6. 01 Err-Proc-Address USAGE PROGRAM-POINTER.
- 7. PROCEDURE DIVISION.
- 8. S1.
- 9. DISPLAY 'Program is starting'
- 10. SET Err-Proc-Address TO ENTRY 'ErrProc'
- 11. CALL 'CBL\_ERROR\_PROC' USING 0, Err-Proc-Address
- 12. CALL 'Tilt' \*> THIS DOESN'T EXIST!!!!
- 13. DISPLAY 'Program is stopping'

```
14.
             STOP RUN
  15.
  16.
         END PROGRAM DemoERRPROC.
  17.
         IDENTIFICATION DIVISION.
  18.
  19.
         PROGRAM-ID. ErrProc.
  20.
         PROCEDURE DIVISION.
  21. 000-Main.
             DISPLAY 'Error: ' FUNCTION EXCEPTION-LOCATION
  22.
  23.
             {\tt DISPLAY} \ \ , \qquad \qquad \text{'} \ \ {\tt FUNCTION} \ \ {\tt EXCEPTION-STATEMENT}
  24.
            DISPLAY '
                             ' FUNCTION EXCEPTION-FILE
                             ' FUNCTION EXCEPTION-STATUS
  25.
            DISPLAY '
  26.
            DISPLAY '*** Returning to Standard Error Routine ***'
  27.
             EXIT PROGRAM
  28.
  29.
         END PROGRAM ErrProc.
When executed, this sample program generates the following console output.
  E:\Programs\Demos>demoerrproc
  Program is starting
  Error: DemoERRPROC; S1; 12
         CALL
         00
         EC-PROGRAM-NOT-FOUND
  *** Returning to Standard Error Routine ***
  DEMOERRPROC.cbl: 27: libcob: Cannot find module 'Tilt'
  E:\Programs\Demos>
```

8.2.26. CBL\_EXIT\_PROC

CBL\_EXIT\_PROC Built-In Subroutine Syntax

```
CALL "CBL_EXIT_PROC" USING function, program-pointer
```

This routine registers a general exit-handling routine.

The function argument must be a numeric literal or a 32-bit binary data item (USAGE BINARY-LONG, for example) with a value of 0 or 1. A value of 0 means that you will be registering ("installing") an exit procedure while a value of 1 indicates you're deregistering ("uninstalling") a previously-installed exit procedure.

The program-pointer must be a data item with a USAGE (see [USAGE], page 198) of PROGRAM-POINTER containing the address of your exit procedure.

A success (0) or failure (non-0) result will be passed back in the RETURN-CODE special register (see [Special Registers], page 227).

An exit procedure, once registered, will trigger whenever a STOP RUN statement (see [STOP], page 345) or a GOBACK statement (see [GOBACK], page 287) is executed anywhere in the program. The exit procedure may execute whatever code is desired to undertake an orderly shut down of the program. Once the exit procedure terminates by executing an EXIT PROGRAM statement (see [EXIT], page 282) or a GOBACK statement, the system-standard program termination routine will be executed.

Only one user-defined exit procedure may be in effect at any time.

The following is a sample GnuCOBOL program that registers an exit procedure. The output of that program is shown as well.

```
IDENTIFICATION DIVISION.
PROGRAM-ID. demoexitproc.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 Exit-Proc-Address
                                 USAGE PROGRAM-POINTER.
PROCEDURE DIVISION.
000-Register-Exit-Proc.
    SET Exit-Proc-Address TO ENTRY "ExitProc"
    CALL "CBL_EXIT_PROC" USING O, Exit-Proc-Address
    IF RETURN-CODE NOT = 0
        DISPLAY 'Error: Could not register Exit Procedure'
    END-IF
099-Now-Test-Exit-Proc.
    DISPLAY
        'Executing a STOP RUN...'
    END-DISPLAY
    GOBACK.
END PROGRAM demoexitproc.
IDENTIFICATION DIVISION.
PROGRAM-ID. ExitProc.
DATA DIVISION.
```

```
WORKING-STORAGE SECTION.
WORKING-SIGNAL
O1 Display-Date
O1 Display-Time
                               PIC XXXX/XX/XX.
PIC XX/XX/XX.
PIC X(8).
01 Now
01 Today
                                PIC X(8).
PROCEDURE DIVISION.
000-Main.
    DISPLAY '*** STOP RUN has been executed ***'
    ACCEPT Today FROM DATE YYYYMMDD
    ACCEPT Now FROM TIME
    MOVE Today TO Display-Date
    MOVE Now TO Display-Time
    INSPECT Display-Time REPLACING ALL '/' BY ':'
    DISPLAY '*** 'Display-Date ' 'Display-Time ' ***'
    GOBACK.
END PROGRAM ExitProc.
```

8.2.27. CBL\_FLUSH\_FILE

CBL_FLUSH_FILE Built-In Subroutine Syntax

CALL "CBL\_FLUSH\_FILE" USING file-handle

In Micro Focus COBOL, calling this subroutine flushes any as-yet unwritten buffers for the (output) file whose file-handle is specified as the argument to disk.

This routine is non-functional in GnuCOBOL. It exists only to provide compatibility for applications that may have been developed for Micro Focus COBOL.

8.2.28. CBL\_GC\_FORK

CBL\_GC\_FORK Built-In Subroute Syntax

```
CALL "CBL_GC_FORK" USING Child-PID
```

CBL\_GC\_FORK allows you to fork the current COBOL process to a new one.

The current content of the process's storage (including LOCAL-STORAGE) will be identical, any file handles get invalid in the new process, positions and file and record locks are only available to the original process.

This system routine is not available on Windows (exception: GCC on Cygwin).

Parameters: none

Returns: pid (the child process gets '0' returned, the calling process gets the pid of the created child).

Negative values are returned for system dependant error codes and -1 if the function is not available on the current system.

CBL\_GC\_FORK allows you to fork the current COBOL process to a new one. The current content of the process' storage (including LOCAL-STORAGE) will be identical, any file handles get invalid in the new process, positions and file / record locks are only available to the original process. This system routine is not available on Windows (exception: gcc on Cygwin). Parameters: none Returns: pid (the child process gets 0 returned, the calling process gets the pid of the created children). Negative values are returned for system dependant error codes and -1 if the function is not available on the current system.

```
IDENTIFICATION DIVISION.
PROGRAM-ID. prog.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 CHILD-PID
                 PIC S9(9) BINARY.
01 WAIT-STS
                   PIC S9(9) BINARY.
PROCEDURE DIVISION.
    CALL
             "CBL_GC_FORK" RETURNING CHILD-PID END-CALL
    EVALUATE TRUE
             WHEN CHILD-PID = ZERO
                  PERFORM CHILD-CODE
             WHEN CHILD-PID > ZERO
                  PERFORM PARENT-CODE
             WHEN CHILD-PID = -1
                  DISPLAY 'CBL_GC_FORK is not available on the current'
                  'system!'
                  PERFORM CHILD-CODE
                  MOVE O TO CHILD-PID
                  PERFORM PARENT-CODE
             WHEN OTHER
                  MULTIPLY -1 BY CHILD-PID END-MULTIPLY
                  DISPLAY 'CBL_GC_FORK returned system error: 'CHILD-PID
    END-EVALUATE
    STOP
             RUN.
```

END-EVALUATE.

```
CHILD-CODE.
            "C$SLEEP" USING 1 END-CALL
   CALL
   DISPLAY "Hello, I am the child"
   MOVE 2 TO RETURN-CODE.
PARENT-CODE.
   DISPLAY "Hello, I am the parent"
           "CBL_GC_WAITPID" USING CHILD-PID RETURNING WAIT-STS
   CALL
   MOVE O TO RETURN-CODE
   EVALUATE TRUE
            WHEN WAIT-STS >= 0
                 DISPLAY 'Child ended with status: 'WAIT-STS
            WHEN WAIT-STS = -1
                 DISPLAY 'CBL_GC_WAITPID is not available on the '
                 'current system!'
            WHEN WAIT-STS < -1
                 MULTIPLY -1 BY WAIT-STS END-MULTIPLY
                 DISPLAY 'CBL_GC_WAITPID returned system error: 'WAIT-STS
```

8.2.29. CBL\_GC\_GETOPT

$CBL\_GC\_GETOPT\ Built-In\ Subroutine\ Syntax$

```
CALL "CBL_GC_GETOPT" USING BY REFERENCE SHORTOPTIONS LONGOPTIONS LONGIND

WALUE LONG-ONLY

BY REFERENCE RETURN-CHAR OPT-VAL
```

CBL\_GC\_GETOPT adapts the well-known option parser, getopt, to GnuCOBOL.

The usage of this system routine is described by the following example.

```
IDENTIFICATION DIVISION.
PROGRAM-ID. PROG.
DATA DIVISION.
WORKING-STORAGE SECTION.
78 SHORTOPTIONS VALUE "jkl".
01 LONGOPTIONS.
    O5 OPTIONRECORD OCCURS 2 TIMES.
       10 OPTIONNAME PIC X(25).
       10 HAS-VALUE PIC 9.
      10 VALPOINT POINTER VALUE NULL.
       10 RETURN-VALUE PIC X(4).
01 LONGIND
                     PIC 99.
O1 LONG-ONLY
                      PIC 9 VALUE 1.
01 RETURN-CHAR
                       PIC X(4).
   OPT-VAL
01
                       PIC X(10).
                       PIC 9 VALUE 0.
   COUNTER
```

We first need to define the necessary fields for getopt's shortoptions, longoptions, longoption index (longind), long-only-option (long-only) and also the fields for return values return-char and opt-val (arbitrary size with trimming, see return codes).

The **shortoptions** are written down as an alphanumeric field (i.e., a string with arbitrary size) as follows:

```
"ab:c::d"
```

This means we want getopt to look for short options named 'a', 'b', 'c' or 'd', require an option value for 'b', and accept an optional one for 'c'.

The longoptions are defined as a table of records with oname, has-value, valpoint and ${\tt val.}^1$

oname defines the name of a longoption. has-value defines if an option value is demanded (has-val = 1), optional (has-val = 2) or not required (has-val = 0).

valpoint is a pointer used to specify an address to save getopt's return value to. The pointer is optional. If it is NULL, getopt returns a value as usual. If you use the pointer it has to point to a PIC X(4) field. The field val is a PIC X(4) character which is returned if the longoption was recognized.

The longoption structure is immutable! You can only vary the number of records.

<sup>&</sup>lt;sup>1</sup> Say what? the discussion and code seem to have diverged.

Now we have the tools to run CBL\_GC\_GETOPT within the procedure division.

```
PROCEDURE DIVISION.
              "version" to OPTIONNAME (1).
     MOVE
     MOVE
              O TO HAS-VALUE (1).
     MOVE
              'V' TO RETURN-VALUE (1).
              "verbose" TO OPTIONNAME (2).
     MOVE
     MOVE.
              O TO HAS-VALUE (2).
     MOVE
              'V' TO RETURN-VALUE (2).
     PERFORM WITH TEST AFTER UNTIL RETURN-CODE = -1
              CALL 'CBL_GC_GETOPT' USING
                  BY REFERENCE SHORTOPTIONS LONGOPTIONS LONGIND
                  BY VALUE LONG-ONLY
                  BY REFERENCE RETURN-CHAR OPT-VAL
              END-CALL
              DISPLAY RETURN-CHAR END-DISPLAY
              DISPLAY OPT-VAL END-DISPLAY
     END-PERFORM
     STOP RUN.
```

The example shows how we initialize all parameters and call the routine until CBL\_GC\_GETOPT runs out of options and returns -1.

return-char might contain the following regular character if an option was recognized:

- ? undefined or ambiguous option
 1 non-option (only if first byte of so is '-')
 0 valpoint != NULL and we are writing the return value to the specified address
 -1 no more options (or reach the first non-option if first byte of shortoptions is '+')
 The return-codes of CBL\_GC\_GETOPT are:
- a non-option (only if first byte of so is '-')
- 0 valpoint != NULL and we are writing the return value to the specified address
- -1 no more options (or reach the first non-option if first byte of shortoptions is '+')
- 2 truncated option value in opt-val (because opt-val was too small)
- 3 a regular answer from getopt

8.2.30. CBL\_GC\_HOSTED

CBL\_GC\_HOSTED Built-In Subroutine Syntax

```
CALL "CBL_GC_HOSTED" USING ARG-1 ARG-2
```

Note replaces CBL\_OC\_HOSTED which is kept as a legacy item.

CBL\_GC\_HOSTED provides access to the following C hosted variables:

```
argc binary-long by value
argv pointer to char **
stdin, stdout, stderr
pointer
```

errno giving address of errno in pointer to binary-long, use based for more

Direct access and conditional access to the following variables:

```
tzname pointer to pointer to array of two char pointers timezone C long, will be seconds west of UTC
```

daylight C int, will be 1 during daylight savings

The system will need HAVE TIMEZONE defined for these to return anything meaningful. Attempts made when they are not available will return 1 from CBL GC HOSTED.

It returns 0 when match, 1 on failure, case matters as does length, "arg" won't match.

The usage of this system routine is described by the following example.

```
IDENTIFICATION DIVISION.
PROGRAM-ID. HOSTED.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 Argc
                BINARY-LONG.
01 Argv
                POINTER.
01 Stdin
               POINTER.
01 Stdout
                POINTER.
01 Stderr
                POINTER.
01 Errno
                POINTER.
01 Err
                BINARY-LONG BASED.
01 Domain
               FLOAT-LONG VALUE 3.0.
01 Tzname POINTER.
01 Tznames POINTER BASED.
05 Tzs POINTER OCCURS
               POINTER OCCURS 2.
01 Timezone
                BINARY-LONG.
                 BINARY-SHORT.
01 Daylight
*>
PROCEDURE DIVISION.
          "CBL_GC_HOSTED" using stdin "stdin"
     display "stdin: " stdin
```

```
call
              "feof" using by value stdin
     display "feof stdin : " return-code
              "CBL_GC_HOSTED" using stdout "stdout"
     call
             "stdout : " stdout
     display
              "fprintf" using by value stdout by content "Hello" & x"Oa"
     call
              "CBL_GC_HOSTED" using stderr "stderr"
     call
     display "stderr : " stderr
     call
              "fprintf" using by value stderr by content "on err" & x"0a"
              "CBL_GC_HOSTED" using argc "argc"
     call
     display "argc : " argc
     call
              "CBL_GC_HOSTED" using argv "argv"
              "argv : " argv
     display
              "args" using by value argc argv
     call
     call
              "CBL_GC_HOSTED" using errno "errno"
     display "&errno : " errno
              address of err to errno
     set
     display "errno : " err
              "acos" using by value domain
     call
     display "errno after acos(3.0): " err ", EDOM is 33"
              "CBL_GC_HOSTED" using argc "arg"
     call
     display "'arg' lookup : " return-code
              "CBL_GC_HOSTED" using null "argc"
     call
     display "null with argc : " return-code
     display "argc is still : " argc
*> the following only returns zero if the system has HAVE_TIMEZONE set
              "CBL_GC_HOSTED" using daylight "daylight "
     call
     display "'timezone' lookup : " return-code
     if
              return-code not = 0
              display "system doesn't has timezone"
     else
              display "timezone is : " timezone
              call "CBL_GC_HOSTED" using daylight "daylight "
              display "'daylight' lookup : " return-code
              display "daylight is : " daylight
              set environment "TZ" to "PST8PDT"
              call static "tzset" returning omitted on exception
                        continue end-call
              call "CBL_GC_HOSTED" using tzname "tzname"
              display "'tzname' lookup : " return-code
*> tzs(1) will point to z"PST" and tzs(2) to z"PDT"
              if
                   return-code equal 0 and tzname not equal null then
                   set address of tznames to tzname
                        tzs(1) not equal null then
                        display "tzs #1 : " tzs(1)
                   end-if
                        tzs(2) not equal null then
                        display "tzs #2 : " tzs(2)
                   end-if
              end-if
     end-if
     goback.
```

end program hosted.

Note that the legacy name of this routine that starts with CBL_OC is deprecated, as is NANOSLEEP but will still work. It is recommended that all library routines names starting with CBL_OC are replaced with CBL_OC to minimise issues.

8.2.31. CBL\_GC\_NANOSLEEP

CBL\_GC\_NANOSLEEP Built-In Subroutine Syntax

CALL "CBL\_GC\_NANOSLEEP" USING nanoseconds-to-sleep

Note replaces CBL\_OC\_NANOSLEEP which is kept as a legacy item.

\_\_\_\_\_

This subroutine puts the program to sleep for the specified number of nanoseconds.

The effective granularity of nanoseconds-to-sleep values will depend upon the granularity of the system clock your computer is using and the timing granularity of the operating system that computer is running.

For example, you will not expect to see any difference between values of 1, 100, 500 or 1000, but you should see a difference between values such as 250000000 and 500000000.

The nanoseconds-to-sleep argument is a numeric literal or data item.

There are one *billion* nanoseconds in a second, so if you wanted to put the program to sleep for 1/4 second you'd use a *nanoseconds-to-sleep* value of 250000000.

Note that the legacy name of this routine starts with "CBL\_OC" is deprecated, as is HOSTED, but will still work. It is recommended that all library routines names starting with "CBL\_OC" are replaced with "CBL\_GC" to minimise issues.

8.2.32. CBL\_GC\_PRINTABLE

CBL\_GC\_PRINTABLE Built-In Subroutine Syntax

CALL "CBL\_GC\_PRINTABLE" USING data-item [, char]

Note replaces C\$PRINTABLE which is kept as a legacy item.

The CBL\_GC\_PRINTABLE subroutine converts the contents of the data-item specified as the first argument to printable characters.

Those characters that are deemed printable (as defined by the character set used by dataitem) will remain unchanged, while those that are not printable will be converted to the character specified as the second argument.

If no *char* argument is provided, a period ('.') will be used.

8.2.33. CBL\_GC\_WAITPID

$CBL\_GC\_WAITPID$ Built-In Subroutine Syntax

CALL "CBL\_GC\_WAITPID" USING ARG-1

RETURNING RET-STATUS

CBL\_GC\_WAITPID allows you to wait until another system process ended.

Additionally you can check the process's return code.

Parameters: none

Returns: function-status / child-status

Negative values are returned for system dependant error codes and -1 if the function is not available on the current system.

CALL "CBL\_GC\_WAITPID" USING CHILD-PID RETURNING WAIT-STS

MOVE O TO RETURN-CODE

DISPLAY 'CBL\_GC\_WAITPID ended with status: 'WAIT-STS

8.2.34. CBL\_GET\_CSR\_POS

CBL\_GET\_CSR\_POS Built-In Subroutine Syntax

CALL "CBL\_GET\_CSR\_POS" USING cursor-locn-buffer

This subroutine will retrieve the current cursor location on the screen, returning a 2-byte value into the supplied *cursor-locn-buffer*. The first byte of *cursor-locn-buffer* will receive the current line (row) location while the second receives the current column location.

The returned location data will be in binary form, and will be based upon starting values of 0, meaning that if the cursor is located at line 15, column 12 at the time this routine is called, a value of (14,11) will be returned.

The following is a typical cursor-locn-buffer definition:

01 CURSOR-LOCN-BUFFER.

05 CURSOR-LINE USAGE BINARY-CHAR.
05 CURSOR-COLUMN USAGE BINARY-CHAR.

Values of 1 (Line) and 1 (column) will be returned if GnuCOBOL was not generated to include screen I/O.

8.2.35. CBL\_GET\_CURRENT\_DIR

$CBL\_GET\_CURRENT\_DIR\ Built-In\ Subroutine\ Syntax$

```
CALL "CBL_GET_CURRENT_DIR" USING BY VALUE 0,

BY VALUE length,

BY REFERENCE buffer
```

This retrieves the fully-qualified pathname of the current directory, saving up to *length* characters of that name into *buffer*.

The first argument is unused, but must be specified. It must be specified BY VALUE (see [CALL], page 253).

The *length* argument must be specified BY VALUE. The *buffer* argument must be specified BY REFERENCE.

The value specified for the *length* argument (a numeric literal or data item) should not exceed the actual length of *buffer* argument.

If the value specified for the *length* argument is LESS THAN the actual length of *buffer* argument, the current directory path will be left-justified and space filled within the first *length* bytes of *buffer* — any bytes in *buffer* after that point will be unchanged.

If the routine is successful, a value of 0 will be returned to the RETURN-CODE special register (see [Special Registers], page 227). If the routine failed because of a problem with an argument (such as a negative or 0 length), a value of 128 will result. Finally, if the 1<sup>st</sup> argument value is anything but zero, the routine will fail with a 129 value.

8.2.36. CBL\_GET\_SCR\_SIZE

CBL\_GET\_SCR\_SIZE Built-In Subroutine Syntax

CALL "CBL\_GET\_SCR\_SIZE" USING no-of-lines, no-of-cols

Use this subroutine to retrieve the current console screen size.

When the system is running in a windowed environment, this will be the sizing of the console window in which the program is executing. When the system is not running a windowing environment, the physical console screen attributes will be returned. In environments such as a Windows console window, where the logical size of the window may far exceed that of the physical console window, the size returned will be that of the physical console window. Two one-byte values will be returned — the first will be the current number of lines (rows) while the second will be the number of columns.

The returned size data will be in binary form.

The following are typical no-of-lines and no-of-columns definitions:

01 NO-OF-LINES USAGE BINARY-CHAR. 01 NO-OF-COLUMNS USAGE BINARY-CHAR.

GnuCOBOL run-time screen management must have been initialized prior to CALLing this routine in order to receive meaningful values. This means that a DISPLAY data-item statement (see [DISPLAY data-item], page 268) or a ACCEPT data-item statement (see [ACCEPT data-item], page 234) must have been executed prior to executing the CALL statement.

Zero values will be returned if the screen has not been initialized and values of 24 (lines) and 80 (columns) will be returned if GnuCOBOL was not generated to include screen I/O.

8.2.37. CBL\_IMP

CBL\_IMP Built-In Subroutine Syntax

CALL "CBL\_IMP" USING item-1, item-2, BY VALUE byte-length

| Old
Arg 1
Bit | Old
Arg 2
Bit | New Arg 2 Bit ===== | This subroutine performs a bit-by-bit logical <i>implies</i> process between the left-most 8*byte-length corresponding bits of <i>item-1</i> and <i>item-2</i> , storing the resulting bit string into <i>item-2</i> . The truth table shown to the left documents the IMP process. |
|---------------------|---------------------|---------------------|---|
| 0 | 0 | 1 | • |
| 0 | 1 | 1 | The item-1 argument may be an alphanumeric literal or a data |
| 1 | 0 | 0 | item and item-2 must be a data item. The length of both item-1 |
| 1 | 1 | 1 | and item-2 must be at least 8*byte-length. |

The byte-length argument may be a numeric literal or data item, and must be specified using BY VALUE (see [CALL], page 253).

Any bits in item-2 after the 8\*byte-length point will be unaffected.

8.2.38. CBL\_NIMP

CBL\_NIMP Built-In Subroutine Syntax

CALL "CBL\_NIMP" USING item-1, item-2, BY VALUE byte-length

| Old
Arg 1
Bit | Old
Arg 2
Bit | New
Arg 2
Bit | This subroutine performs the <i>negation</i> of a bit-by-bit logical plies process between the left-most 8*byte-length corresponsits of item-1 and item-2, storing the resulting bit string |
|---------------------|---------------------|---------------------|---|
| ===== | ===== | ===== | item-2. The truth table shown to the left documents the N |
| 0 | 0 | 0 | process. |
| 0 | 1 | 0 | |
| 1 | 0 | 1 | The item-1 argument may be an alphanumeric literal or a c |
| 1 | 1 | 0 | item and item-2 must be a data item. The length of both ite |
| | | | and item-2 must be at least 8*byte-length. |

The *byte-length* argument may be a numeric literal or data item, and must be specified using BY VALUE (see [CALL], page 253).

Any bits in item-2 after the 8\*byte-length point will be unaffected.

8.2.39. CBL\_NOR

CBL\_NOR Built-In Subroutine Syntax

CALL "CBL\_NOR" USING item-1, item-2, BY VALUE byte-length

| | | |
|---------------------|---------------------|--|
| Old
Arg 2
Bit | New
Arg 2
Bit | This subroutine performs the negation of a bit-by-bit logical or' process between the left-most 8*byte-length corresponding bits of item-1 and item-2, storing the resulting bit string into item-2. |
| ===== | ===== | The truth table shown to the left documents the NOR process. |
| 0 | 1 | |
| 1 | 0 | The item-1 argument may be an alphanumeric literal or a data |
| 0 | 0 | item and item-2 must be a data item. The length of both item-1 |
| 1 | 0 | and item-2 must be at least 8*byte-length. |
| | Arg 2 Bit 0 1 | Arg 2 Arg 2 Bit Bit ==== 0 1 1 0 0 0 |

The byte-length argument may be a numeric literal or data item, and must be specified using BY VALUE (see [CALL], page 253).

Any bits in item-2 after the 8\*byte-length point will be unaffected.

8.2.40. CBL\_NOT

CBL\_NOT Built-In Subroutine Syntax

CALL "CBL\_NOT" USING item-1, BY VALUE byte-length

This subroutine "flips" the left-most 8\*byte-length bits of item-1, changing 0 bits to 1, and 1 bits to 0. The changes are made directly im item-1.

The item-1 argument must be a data item. The length of item-1 must be at least 8\*byte-length.

The *byte-length* argument may be a numeric literal or data item, and must be passed using BY VALUE (see [CALL], page 253).

Any bits in item-1 after the 8\*byte-length point will be unaffected.

8.2.42. CBL\_OPEN\_FILE

CBL\_OPEN\_FILE Built-In Subroutine Syntax

CALL "CBL\_OPEN\_FILE" USING file-path, access-mode, 0, 0, handle

This routine opens an existing file for use as a byte-stream file usable by CBL\_WRITE\_FILE or CBL\_READ\_FILE.

The file-path argument is an alphanumeric literal or data-item.

The access-mode argument is a numeric literal or data item with a PIC X USAGE COMP-X (or USAGE BINARY-CHAR) definition; it specifies how you wish to use the file, as follows:

- input (read-only)
- 2 output (write-only)
- 3 input and/or output

The third and fourth arguments would specify a locking mode and device specification, respectively, but they're not implemented in GnuCOBOL (currently, at least) — just specify each as 0.

The final argument (handle) is a PIC X(4) USAGE COMP-X item that will receive the handle to the file. That handle is used on all other byte-stream functions to reference this specific file.

A RETURN-CODE special register (see [Special Registers], page 227) value of -1 indicates an invalid argument, while a value of 0 indicates success. A value of 35 means the file does not exist.

8.2.43. CBL\_OR

$CBL_{-}OR$ Built-In Subroutine Syntax

CALL "CBL\_OR" USING item-1, item-2, BY VALUE byte-length

| Old
Arg 1
Bit | Old
Arg 2
Bit | New
Arg 2
Bit | This subroutine performs a bit-by-bit logical or process between
the left-most 8*byte-length corresponding bits of item-1 and
item-2, storing the resulting bit string into item-2. The truth |
|---------------------|---------------------|---------------------|---|
| ===== | ===== | ===== | table shown to the left documents the OR process. |
| 0 | 0 | 0 | 1 |
| 0 | 1 | 1 | The item-1 argument may be an alphanumeric literal or a data |
| 1 | 0 | 1 | item and item-2 must be a data item. The length of both item-1 |
| 1 | 1 | 1 | and item-2 must be at least 8*byte-length. |

The byte-length argument may be a numeric literal or data item, and must be specified using BY VALUE (see [CALL], page 253).

Any bits in item-2 after the 8\*byte-length point will be unaffected.

8.2.44. CBL\_READ\_FILE

CBL\_READ\_FILE Built-In Subroutine Syntax

CALL "CBL\_READ\_FILE" USING handle, offset, nbytes, flag, buffer

This routine reads *nbytes* of data starting at byte number *offset* from the byte-stream file defined by *handle* into *buffer*.

The handle argument (PIC X(4) USAGE COMP-X) must have been populated by a prior call to CBL\_OPEN\_FILE built-in system subroutine (see [CBL\_OPEN\_FILE], page 523).

The offset argument (PIC X(8) USAGE COMP-X) defines the location in the file of the first byte to be read. The first byte of a file is byte offset 0.

The *nbytes* argument (PIC X(4) USAGE COMP-X) specifies how many bytes (maximum) will be read. If the *flag* argument is specified as 128, the size of the file (in bytes) will be returned into the file offset argument (argument 2) upon completion. Not all operating system/GnuCOBOL environments may be able to retrieve file sizes in such cases, a value of zero will be returned. The only other valid value for flags is 0. This argument may be specified either as a numeric literal or as a PIC X USAGE COMP-X data item.

Upon completion, the RETURN-CODE special register (see [Special Registers], page 227) will be set to 0 if the read was successful or to 10 if an "end-of-file" condition occurred. If a value of -1 is returned, a problem was identified with the subroutine arguments.

8.2.45. CBL\_READ\_KBD\_CHAR

CBL\_READ\_KBD\_CHAR Build-In Subroutine Syntax

CALL "CBL\_READ\_KBD\_CHAR" USING char RETURNING status-code.

Waits until a character is typed from the terminal and then read it with no echo.

Parameters: char PIC X. Receives the character that was typed, in ASCII. status-code PIC XX COMP-5.

If RETURNING is not used the RETURN-CODE special register receives the status-code where zero is success and non-zero it is not.

[Above information taken from MF WB manual].

8.2.46. CBL\_RENAME\_FILE

CBL\_RENAME\_FILE Built-In Subroutine Syntax

CALL "CBL\_RENAME\_FILE" USING old-file-path, new-file-path

You may use this subroutine to rename a file.

The file specified by *old-file-path* will be "renamed" to the name specified as *new-file-path*. Each argument may be an alphanumeric literal or data item.

Despite what the name of this routine might make you believe, this routine is more than just a simple "rename" — it will actually move the file supplied as the 1<sup>st</sup> argument to the file specified as the 2nd argument. Think of it as a two-step sequence, first copying the *old-file-path* file to the *new-file-path* file and then a second step where the *old-file-path* is deleted.

If the attempt to move the file fails (for example, it doesn't exist), the RETURN-CODE special register (see [Special Registers], page 227) will be set to 128; on successful completion it will be set to 0.

8.2.47. CBL\_SET\_CSR\_POS

CBL\_SET\_CSR\_POS Build-In Subroutine Syntax

CALL "CBL\_SET\_CSR\_POS" USING cursor-locn-buffer

Set current cursor position on terminal.

This subroutine will set the cursor location on the screen, using a 2-byte value into the supplied *cursor-locn-buffer*. The first byte of *cursor-locn-buffer* is for the line (row) location while the second sets the column location.

The two byte data block must be in binary form, and will be based upon starting values of 0, meaning that if the routine is called with a value of (14,11) cursor will be located at line 15, column 12.

The following is a typical cursor-locn-buffer definition:

01 CURSOR-LOCN-BUFFER.

05 CURSOR-LINE USAGE BINARY-CHAR.
05 CURSOR-COLUMN USAGE BINARY-CHAR.

8.2.48. CBL\_TOLOWER

CBL\_TOLOWER Built-In Subroutine Syntax

CALL "CBL\_TOLOWER" USING data-item, BY VALUE convert-length

This routine will convert the first *convert-length* (a numeric literal or data item) characters of data-item (an alpha-numeric identifier) to lower-case.

The *convert-length* argument must be specified BY VALUE (see [CALL], page 253). It specifies how many (leading) characters in data-item will be converted — any characters after that will remain unchanged.

If convert-length is negative or zero, no conversion will be performed.

8.2.49. CBL\_TOUPPER

$\mathbf{CBL}_{-}\mathbf{TOUPPER}\ \mathbf{Built-In}\ \mathbf{Subroutine}\ \mathbf{Syntax}$

CALL "CBL\_TOUPPER" USING data-item, BY VALUE convert-length

This routine will convert the first *convert-length* (a numeric literal or data item) characters of *data-item* (an alpha-numeric identifier) to upper-case.

The convert-length argument must be specified BY VALUE (see [CALL], page 253). It specifies how many (leading) characters in data-item will be converted — any characters after that will remain unchanged.

If convert-length is negative or zero, no conversion will be performed.

8.2.50. CBL\_WRITE\_FILE

CBL\_WRITE\_FILE Built-In Subroutine Syntax

CALL "CBL\_WRITE\_FILE" USING handle, offset, nbytes, 0, buffer

This routine writes *nbytes* of data from *buffer* to the byte-stream file defined by *handle* starting at byte number *offset* within the file.

The handle argument (PIC X(4) USAGE COMP-X) must have been populated by a prior call to CBL\_OPEN\_FILE. The offset argument (PIC X(4) USAGE COMP-X) defines the location in the file of the first byte to be written to. The first byte of a file is byte offset 0.

The *nbytes* argument (PIC X(4) USAGE COMP-X) specifies how many bytes (maximum) will be written.

Currently, the only allowable value for the flags argument is 0. This argument may be specified either as a numeric literal or as a PIC X(1) USAGE COMP-X data item.

Upon completion, the RETURN-CODE special register (see [Special Registers], page 227) will be set to 0 if the write was successful or to 30 if an I/O error condition occurred. If a value of -1 is returned, a problem was identified with the subroutine arguments.

8.2.51. CBL\_XOR

CBL\_XOR Built-In Subroutine Syntax

CALL "CBL\_XOR" USING item-1, item-2, BY VALUE byte-length

| Old
Arg 1 | Old
Arg 2 | New
Arg 2 | This subroutine performs a bit-by-bit logical $exclusive\ or$ process between the left-most $8*byte-length$ corresponding bits of $item$ - |
|--------------|--------------|--------------|--|
| Bit | Bit | Bit | 1 and item-2, storing the resulting bit string into item-2. The |
| ===== | ===== | ===== | truth table shown to the left documents the XOR process. |
| 0 | 0 | 0 | |
| 0 | 1 | 1 | The item-1 argument may be an alphanumeric literal or a data |
| 1 | 0 | 1 | item and item-2 must be a data item. The length of both item-1 |
| 1 | 1 | 0 | and item-2 must be at least 8*byte-length. |

The byte-length argument may be a numeric literal or data item, and must be specified using BY VALUE (see [CALL], page 253).

Any bits in item-2 after the 8\*byte-length point will be unaffected.

A result of zero will be passed back in the RETURN-CODE special register (see [Special Registers], page 227).

8.2.52. SYSTEM

SYSTEM Built-In Subroutine Syntax

CALL "SYSTEM" USING command

This subroutine submits *command* (an alphanumeric literal or data item) to a command shell for execution as if it were typed into a console/terminal window.

A shell will be opened subordinate to the GnuCOBOL program issuing the call to SYSTEM.

Output from the command (if any) will appear in the command window in which the Gnu-COBOL program was executed.

On a Unix system, the shell environment will be established using the default shell program. This is also true when using a GnuCOBOL build created with and for OSX or the Cygwin Unix emulator.

With native Windows Windows/MinGW builds, the shell environment will be the Windows console window command processor (usually cmd.exe) appropriate for the version of Windows you're using.

To trap output from the executed command and process it within the GnuCOBOL program, use a redirection ('>') to send the command output to a temporary file which you read from within the program once control returns.

The exit status of the executed command will be available in the RETURN-CODE special-register.

8.2.53. X"91"

X"91" Built-In Subroutine Syntax

CALL X"91" USING return-code, function-code, binary-variable-arg

The original Micro Focus version of this routine is capable of providing a wide variety of functions. GnuCOBOL supports just three of them:

- Turning runtime switches (SWITCH-1, ..., SWITCH-8) on.
- Turning runtime switches (SWITCH-1, ..., SWITCH-8) off.
- Retrieving the number of arguments passed to a subroutine.

The return-code argument must be a one-byte binary numeric data item (USAGE BINARY-CHAR is recommended). It will receive a value of 0 if the operation was successful, 1 otherwise.

The function-code argument must be either a numeric literal or a one-byte binary numeric data item (USAGE BINARY-CHAR is recommended).

The third argument — variable-arg — is defined differently depending upon the function-code value, as follows:

Sets and/or clears all eight of the COBOL switches (SWITCH-1 through SWITCH-8). See [SPECIAL-NAMES], page 84, for an explanation of those switches.

The variable-arg argument should be an OCCURS 8 TIMES table of USAGE BINARY-CHAR.

Each occurrence that is set to a value of zero prior to the CALL X"91" will cause the corresponding switch to be cleared. Each occurrence set to 1 prior to the CALL X"91" will cause the corresponding switch to be set.

Values other than 0 or 1 will be ignored.

12 Reads all eight of the COBOL switches (SWITCH-1 through SWITCH-8)

The variable-arg argument should be an OCCURS 8 TIMES table of USAGE BINARY-CHAR.

Each of the 1^{st} eight occurrences of the array will be set to either 0 or 1-1 if the corresponding switch is set, 0 otherwise.


Retrieves the number of arguments passed to the program executing the CALL X"91", saving that number into the *variable-arg* argument. That should be a binary numeric data item (USAGE BINARY-CHAR is recommended).

8.2.54. X"E4"

X"E4" Built-In Subroutine Syntax CALL X"E4"

Use X"E4" to clear the screen. There are no arguments and no returned value.

8.2.55. X"E5"



The X"E5" routine will sound the PC "bell". There are no arguments and no returned value.

8.2.56. X"F4"

X"F4" Built-In Subroutine Syntax

CALL X"F4" USING byte, table

This routine packs the low-order (rightmost) bit from each of the eight 1-byte items in table into the corresponding bit positions of the single-byte data item byte.

The *byte* data item need be only a single byte in size. If it is longer, the excess will be unaffected by this subroutine.

The table data item must be at least 8 bytes long. If it is longer, the excess will be ignored by this subroutine.

Typically, table is defined similarly to the following:

01 Table-Arg.

05 Each-Byte OCCURS 8 TIMES USAGE BINARY-CHAR.

8.2.57. X"F5"

X"F5" Built-In Subroutine Syntax CALL X"F5" USING byte, table

This routine unpacks each bit of the single-byte data item byte into the low-order (rightmost) bit of each of the corresponding eight 1-byte items in table. The other seven bit positions of each of the first eight entries in table will be set to zero.

The *byte* data item need be only a single byte in size. If it is longer, the excess will be unaffected by this subroutine.

The *table* data item must be at least 8 bytes long. If it is longer, the excess will be ignored by this subroutine.

Typically, table is defined similarly to the following:

01 Table-Arg. 05 Each-Byte OCCURS 8 TIMES USAGE BINARY-CHAR.

End of Chapter 8 — Functions

9. Report Writer Usage

9.1. RWCS Lexicon

There are a number of terms that describe various aspects of the operation of the Report Writer Control System (RWCS). Understanding the meanings of these terms is vital to developing an understanding of the subject.

Control Break

An event that is triggered when a control field on an RWCS-generated report changes value. It is these events that trigger the generation of control heading and control footing groups.

Control Field

A field of data being presented within a detail group; as the various detail groups that comprise the report are presented, they are presumed to appear in sorted sequence of the control fields contained within them. As an example, a department-by-department sales report for a chain of stores would probably be sorted by store number and – within like store numbers – be further sorted by department number. The store number will undoubtedly serve as a control field for the report, allowing control heading groups to be presented before each sequence of detail groups for the same store and control footing groups to be presented after each such sequence.

Control Footing

A report group that appears immediately after one or more detail groups of an RWCS-generated report. Such are produced automatically as a result of a control break. This type of group typically serves as a summary of the detail group(s) that precede it, as might be the case on a sales report for a chain of stores, where the detail groups documenting sales for each department (one department per detail group) from the same store might be followed by a control footing that provides a summation of the department-by-department sales for that store.

Control Heading

A report group that appears immediately before one or more detail groups of an RWCS-generated report. Such are produced automatically as a result of a control break. This type of group typically serves as an introduction to the detail group(s) that follow, as might be the case on a sales report for a chain of stores, where the detail groups documenting sales for each department (one department per detail group) from the same store might be preceded by a control heading that states the full name and location of the store.

Detail Group

A report group that contains the detailed data being presented for the report.

Page Footing

A report group that appears at the bottom of every page of an RWCS-generated report. Information typically found within such a report group might be:

- The date the report was generated
- The current page number of the report

Page Heading

A report group that appears at the top of every page of an RWCS-generated report. Information typically found within such a report group might be:

• A title for the report

- The date the report was generated
- The current page number of the report
- Column headings describing the fields within the detail group(s)

Report Footing

A report group that occurs only once in an RWCS-generated report — as the very last presented report group of the report. These typically serve as a visual indication that the report is finished.

Report Group

One or more consecutive lines on a report that serve a common informational purpose or function. For example, lines of text that are displayed at the top or bottom of every printed page of a report.

Report Heading

A report group that occurs only once in an RWCS-generated report — as the very first presented report group of the report. These typically serve as an introduction to the report.

9.2. The Anatomy of a Report

Every report has the same basic structure, as shown here, even though not all reports will have all of the groups shown. In fact, it is a very unusual report indeed that actually has every one of these groups:

- REPORT HEADING
- PAGE HEADING [1]
- CONTROL HEADING(S) [2]
- DETAIL GROUP(S) [2]
- CONTROL FOOTING(S) [2]
- FINAL CONTROL FOOTING
- PAGE FOOTING [1]
- REPORT FOOTING
- [1] Presented throughout the report, as needed
- [2] Repeated, as needed

These groups will be presented (printed) across however many formatted pages are necessary to hold them. No single report group will be allowed to cross page boundaries.

The management of paging, enforcement of the *groups cannot span pages* rule and almost every aspect of report generation are handled entirely by the Report Writer Control System.

9.3. The Anatomy of a Report Page

Each page of a report is divided into as many as five (5) areas, as shown in the following diagram.





When describing a report via the RD (see [REPORT SECTION], page 124) clause, the total number of usable lines are specified as the PAGE LIMIT value; this value is the sum of the number of lines contained in the Heading, Body and Footing Areas.

The unusable areas of a page (if any) will appear above and below that usable area. You don't specify the unusable area in the RD, but rather using a LINAGE (see [File/Sort-Description], page 113) clause in the FD of the file the report is "attached" to.

The various report groups will be presentable in the various areas of a page, as follows:

REPORT HEADING

Heading Area — An exception to this is the situation where the report heading report group contains the NEXT GROUP NEXT PAGE (see [NEXT GROUP], page 170) option; in those cases, the report heading will be presented on a page by itself (anywhere on that page) at the beginning of the report.

PAGE HEADING

Heading Area

CONTROL HEADING

Body Area, but no line of a control heading is allowed past the line number specified by LAST CONTROL HEADING

DETAIL Body Area, but no line of a detail report group is allowed past the line number specified by LAST DETAIL

CONTROL FOOTING

Body Area, but no line of a control footing report group is allowed past the line number specified by ${\tt FOOTING}$

PAGE FOOTING

Footing Area

REPORT FOOTING

Footing Area — An exception to this is the situation where the report footing report group contains the NEXT PAGE option in its LINE (see [LINE], page 167) clause; in those cases, the report footing will be presented on a page by itself at the end of the report.

9.4. How RWCS Builds Report Pages

A report created via a WRITE statement (see [WRITE], page 360) will contain carriage-control information. Most notably, ASCII form-feed characters (X'OC') will be written to the report file to support the statement's ADVANCING PAGE option. Whether the data for a report line created

via ADVANCING PAGE occurs before or after the form-feed character depends upon whether the programmer coded WRITE record-name BEFORE ADVANCING PAGE or WRITE record-name AFTER ADVANCING PAGE, respectively.

The GnuCOBOL implementation of RWCS does not issue any carriage-control information to the report files it produces — instead, it relies upon the information coded in the RD for the report (specifically the PAGE LIMITS and related options) and its internally-generated and managed LINE-COUNTER special register (see [Special Registers], page 227) for the report to know when to issue any blank lines to the file to fill-out the end of a printed page.

Because this is the way the GnuCOBOL RWCS works, in order to design an RWCS-generated report you'll need to know answers to the following questions:

- 1. What printer(s) will the report be printed on?
- 2. What paper orientation will you use, Landscape (long edge of the paper at the top and bottom of page), or Portrait (long edge of the paper at the left and right of page)?
- 3. What tool will be used to print the report (direct printing to the device, notepad.exe, MS-Word, ...)?
- 4. What font and font size will be used for the report when it is printed? RWCS-generated reports will assume that a fixed-width font such as "Courier", "Lucida Console", "Consolas" and the like will be used to print, as variable-pitch fonts would make the proper alignment of columns of data on reports virtually impossible.
- 5. When unprintable area exists at all four margins of the paper? These are generally caused by the printer itself or by its software driver.
- 6. What is the maximum number of lines per page that may be printed on a single sheet of paper?
- 7. What is the maximum number of characters that may be printed on one line?

Once you know the answer to questions 1-4, you may easily determine the answers to the remaining questions as follows:

- 1. Prepare a text file containing 100 or so records, each consisting of a numeric scale (123456789012345678901234...).
- 2. Print the file in a manner consistent with your answers to questions 1-4.
- 3. Add any necessary additional digits to each record in your test file (if lines weren't full) or remove characters from the end of each record if lines wrapped. If you made changes, reprint the file.
- 4. Now that you know *exactly* how long each record may be, add additional records and reprint. Continue until printing overflows to a second page.
- 5. The first page you print is now a perfect template to use when designing reports it shows, given the answers to questions 1-4, every available printable character position on a page! The number of lines printed on that page becomes your PAGE LIMIT value for the RD.

The remaining PAGE LIMIT values can be established as required by your report(s).

Using *identifier* rather than *integer* specifications in the RD will give your program the ability — at run time — to accommodate multiple printers, fonts, font sizes and paper orientation. Just follow the above steps for each combination you wish your program to support.

9.5. Control Hierarchy

Every report that employs control breaks has a natural hierarchy of those control breaks based upon the manner in which the data the report is being generated from is sorted. This con-

cept is best understood using an example which assumes a COBOL program to process sales data collected from every computerized cash register across a chain of stores having multiple departments is being developed.

The application that collects data from the various cash registers at each store will generate data records that look like this to a COBOL program:

```
O1 Sales-For-Register.

O5 Sales-Date PIC 9(8).

O5 Time-Collected PIC 9(6).

O5 Register-Number PIC 9(7).

O5 Store-Number PIC 9(3).

O5 Department-Number PIC 9(3).

O5 Total-Sales PIC 9(6)V99.
```

Your task is to develop a report that shows the sales total from each cash register and summarizes those sales by department within each store, by store and also generates a total sales figure for the day across all stores.

To accomplish this, you will use a SORT statement (see [SORT], page 339) to sort the file of cash register sales data into:

- 1. Ascending sequence of store number
- 2. Within each store, data will be sorted into ascending sequence of department number
- 3. If there are multiple cash registers in a particular department of a specific store, the data needs to be further sorted so that the cash registers are ordered in sequence of their register number.

So, assuming a sort file has been defined and its record layout (essentially a mirror of the raw data file) is defined as follows:

```
01 Sorted-Sales-For-Register.
05 Sorted-Sales-Date PIC 9(8).
05 Sorted-Time-Collected PIC 9(6).
05 Sorted-Register-Number PIC 9(7).
05 Sorted-Store-Number PIC 9(3).
05 Sorted-Department-Number PIC 9(3).
05 Sorted-Total-Sales PIC 9(6)V99.
```

Then the SORT statement to accomplish the desired sequencing would be:

```
SORT SORT-FILE

ASCENDING KEY Sorted-Store-Number

Sorted-Department-Number

Sorted-Register-Number

USING Input-file

OUTPUT PROCEDURE 100-Generate-Report
```

As a result of the sort, our program might expect to see data somewhat like this (date, time and sales totals are shown as "..."):

```
...0589130001001...
...0625174001001...
...0122234001002...
...0732345001002...
...0003423001003...
...2038774001004...
...0112646002001...
...9963348002002...
...3245677002003...
...4456778002003...
...0002345002004...
```

Because of the sort, the most-frequently changing value of the three sort keys will be that of Sorted-Register-Number. This essentially defines the "detail" level of the report.

The next most-frequently changing value is that of Sorted-Department-Number, and the least-frequently changing value is that of Sorted-Store-Number. remember that the program should be generating totals each time one of these two values change, plus a grand total of sales at the end of the report. These three points are the *Control Break* points of the report.

When the report is defined, it's RD would contain a CONTROLS ARE clause that lists the control breaks in least- to most-frequent sequence of changing. This would be coded as:

```
CONTROLS ARE FINAL, Sorted-Store-Number, Sorted-Department-Number
```

A FINAL control break only occurs once, at the very end of the report. The CONTROL FOOTING for this break will be the one that produces the grand total of sales for all stores.

The next break listed on the CONTROLS clause will be the one that occurs next most-frequently (Sorted-Store-Number). This control break will be the one that produces the summation for each entire store, and will have its own CONTROL FOOTING.

The next (and last, in this case) break listed on the CONTROLS clause will be the one that occurs even more frequently (Sorted-Department-Number). The CONTROL FOOTING for this control field will be the one that summarizes sales for each department within a store.

This sequence of control breaks from least- to most-frequent (in other words, in the order they occur on the CONTROLS ARE clause) is the 'control hierarchy' of the report; control breaks that occur more frequently than others are said to be at a lower level in the control hierarchy.

Defining a control hierarchy (via CONTROLS ARE) that does not match the actual sequence in which data will be processed is a great way to guarantee a "broken" report. I'll show you an example in a later section.

9.6. An Example

This section contains an example of the RWCS at work. The complete program, presented here, is a stripped-down version of a program I have used to generate a report for a class I teach on PC hardware. This report will provide benchmark statistics on a variety of popular AMD and Intel CPUs. The data for the report was obtained from the website www.cpubenchmark.net in December of 2013. By the time you are reading this, that data will most likely have become rather out of date, but it illustrates RWCS well enough.

9.6.1. Data

Here is the data that the program will be reading. Each record reflects the aggregated benchmark scoring for one particular CPU, as scores for benchmarks against that CPU have been reported to the cpubenchmark.net website by their PassMark benchmark software. The data consists of

four fields. Fields are separated from one another by a single comma. The descriptions of the fields are as follows:

Benchmark Score

A five-digit number showing the aggregated benchmark scores for the CPU; the higher this number, the better the CPU performed in benchmark testing.

Vendor The name of the vendor who makes the CPU. In this data, that will either be "AMD" (American Micro Devices) or "INTEL".

Family The 7-character family of CPU products the CPU falls into. This will have values such as "A4", "A10", "Core i5", "Core i7", etc.

Model The specific model of CPU within the family.

The first record of data shown below shows that the aggregated score of all benchmarks reported for the AMD A10-4600M CPU is 3145, as compared to the second record which shows that the aggregated score reported of all benchmarks reported for the Intel Core-i7-4960X CPU is 14291.

The following is the complete set of input data used for this example. This is by no means the complete set of data available at cpubenchmark.net — it is just a representative sample used for this example. For my class, I give my students a report showing the results for almost a thousand CPUs.

For the sake of brevity, this document lists the data in three columns.

```
03145, AMD, A10, 4600M
                                  05421,AMD,FX,6100
                                                                    03917, Intel, Core i5,4300U
                                  05813,AMD,FX,6120
14291, Intel, Core i7, 4960X
                                                                    01743, Intel, Core i5, 4300Y
02505,AMD,A10,4655M
                                  06194,AMD,FX,6200
                                                                    04804, Intel, Core i5, 4330M
03449, AMD, A10, 4657M
                                  06388,AMD,FX,6300
                                                                    03604, Intel, Core i5, 4350U
04251,AMD,A10,5700
                                  07017, AMD, FX, 6350
                                                                    06282, Intel, Core i5,4430
                                  06163,AMD,FX,8100
                                                                    05954, Intel, Core i5,4430S
02758, AMD, A10, 5745M
03332,AMD,A10,5750M
                                  06605, AMD, FX, 8120
                                                                    06517, Intel, Core i5,4440
03253, AMD, A10, 5757M
                                  06845, AMD, FX, 8140
                                                                    07061, Intel, Core i5, 4570
04798, AMD, A10, 5800B
                                  07719, AMD, FX, 8150
                                                                    06474, Intel, Core i5, 4570R
04677, AMD, A10, 5800K
                                  08131,AMD,FX,8320
                                                                    06803, Intel, Core i5, 4570S
04767,AMD,A10,6700
                                  09067, AMD, FX, 8350
                                                                    02503, Intel, Core i5, 4570T
05062, AMD, A10, 6800K
                                  09807, AMD, FX, 9370
                                                                    07492, Intel, Core i5, 4670
00677,AMD,A4,1200
                                                                    07565, Intel, Core i5, 4670K
                                  10479, AMD, FX, 9590
00559,AMD,A4,1250
                                  03076, Intel, Core i3, 3110M
                                                                    06351, Intel, Core i5, 4670T
01583,AMD,A4,3300
                                                                    03701, Intel, Core i7, 3517U
                                  03301, Intel, Core i3, 3120M
01237,AMD,A4,3300M
                                  03655, Intel, Core i3, 3130M
                                                                    03449, Intel, Core i7, 3517UE
01227,AMD,A4,3305M
                                  03820, Intel, Core i3,3210
                                                                    04588, Intel, Core i7, 3520M
01263,AMD,A4,3310MX
                                  02266, Intel, Core i3, 3217U
                                                                    03912, Intel, Core i7, 3537U
01193,AMD,A4,3320M
                                  04219, Intel, Core i3, 3220
                                                                    04861, Intel, Core i7, 3540M
01343,AMD,A4,3330MX
                                  03724, Intel, Core i3, 3220T
                                                                    04009, Intel, Core i7, 3555LE
01625,AMD,A4,3400
                                  04407, Intel, Core i3,3225
                                                                    06144, Intel, Core i7, 3610QE
01768, AMD, A4, 3420
                                  02575, Intel, Core i3, 3227U
                                                                    07532, Intel, Core i7, 3610QM
01685,AMD,A4,4300M
                                  01885, Intel, Core i3, 3229Y
                                                                    06988, Intel, Core i7, 3612QE
01169,AMD,A4,4355M
                                  04259, Intel, Core i3, 3240
                                                                    06907, Intel, Core i7, 3612QM
                                                                    05495, Intel, Core i7, 3615QE
01919,AMD,A4,5000
                                  03793, Intel, Core i3, 3240T
01973, AMD, A4, 5150M
                                  04414, Intel, Core i3,3245
                                                                    07310, Intel, Core i7, 3615QM
02078,AMD,A4,5300
                                  04757, Intel, Core i3,3250
                                                                    07759, Intel, Core i7, 3630QM
01632, AMD, A4, 5300B
                                  03443, Intel, Core i3,4000M
                                                                    07055, Intel, Core i7, 3632QM
02305,AMD,A4,6300
                                  02459, Intel, Core i3, 4010U
                                                                    06516, Intel, Core i7, 3635QM
01634, AMD, A6, 1450
                                  02003, Intel, Core i3, 4010Y
                                                                    04032, Intel, Core i7, 3667U
01964,AMD,A6,3400M
                                  04904, Intel, Core i3,4130
                                                                    04271, Intel, Core i7, 3687U
02101,AMD,A6,3410MX
                                  04041, Intel, Core i3,4130T
                                                                    03479, Intel, Core i7, 3689Y
02078,AMD,A6,3420M
                                  05115, Intel, Core i3,4330
                                                                    08347, Intel, Core i7, 3720QM
02277, AMD, A6, 3430MX
                                  05117, Intel, Core i3,4340
                                                                    08512, Intel, Core i7, 3740QM
                                  03807, Intel, Core i5, 3210M
01995,AMD,A6,3500
                                                                    09420, Intel, Core i7,3770
02798, AMD, A6, 3600
                                  03995, Intel, Core i5, 3230M
                                                                    09578, Intel, Core i7, 3770K
02892,AMD,A6,3620
                                  03126, Intel, Core i5, 3317U
                                                                    09074, Intel, Core i7, 3770S
```

```
03232,AMD,A6,3650
                                 04101, Intel, Core i5, 3320M
                                                                   08280, Intel, Core i7, 3770T
                                 05902, Intel, Core i5, 3330
03327,AMD,A6,3670
                                                                   08995, Intel, Core i7,3820
01630,AMD,A6,4400M
                                 05690, Intel, Core i5, 3330S
                                                                   08548, Intel, Core i7, 3820QM
01296,AMD,A6,4455M
                                 05781, Intel, Core i5,3335S
                                                                   09025, Intel, Core i7,3840QM
02440,AMD,A6,5200
                                 03280, Intel, Core i5, 3337U
                                                                   09196, Intel, Core i7, 3920XM
01958,AMD,A6,5350M
                                 02252, Intel, Core i5, 3339Y
                                                                   12107, Intel, Core i7, 3930K
01878,AMD,A6,5357M
                                 06282, Intel, Core i5,3340
                                                                   09052, Intel, Core i7, 3940XM
01906,AMD,A6,5400B
                                 04327, Intel, Core i5, 3340M
                                                                   12718, Intel, Core i7, 3960X
02174,AMD,A6,5400K
                                 05372, Intel, Core i5,3340S
                                                                   12823, Intel, Core i7, 3970X
02384,AMD,A6,6400K
                                 06199, Intel, Core i5, 3350P
                                                                   03992, Intel, Core i7, 4500U
                                                                   04507, Intel, Core i7, 4558U
02050,AMD,A8,3500M
                                 04314, Intel, Core i5, 3360M
02426,AMD,A8,3510MX
                                04555, Intel, Core i5,3380M
                                                                   04892, Intel, Core i7, 4600M
02245,AMD,A8,3520M
                                03589, Intel, Core i5,3427U
                                                                   04484, Intel, Core i7, 4600U
02276,AMD,A8,3530MX
                                03479, Intel, Core i5,3437U
                                                                   03680, Intel, Core i7, 4610Y
                                                                   04345, Intel, Core i7, 4650U
02866,AMD,A8,3550MX
                                03057, Intel, Core i5,3439Y
03215,AMD,A8,3800
                                 06442, Intel, Core i5, 3450
                                                                   07352, Intel, Core i7, 4700EQ
03217, AMD, A8, 3820
                                 06071, Intel, Core i5,3450S
                                                                   08161, Intel, Core i7, 4700HQ
                                                                   07946, Intel, Core i7, 4700MQ
03552,AMD,A8,3850
                                 06576, Intel, Core i5,3470
03682,AMD,A8,3870K
                                 06077, Intel, Core i5,3470S
                                                                   08002, Intel, Core i7,4702HQ
02709,AMD,A8,4500M
                                 04591, Intel, Core i5,3470T
                                                                   07647, Intel, Core i7, 4702MQ
02193,AMD,A8,4555M
                                 05991, Intel, Core i5,3475S
                                                                   08066, Intel, Core i7,4750HQ
04052,AMD,A8,5500
                                 06828, Intel, Core i5, 3550
                                                                   07367, Intel, Core i7, 4765T
03464,AMD,A8,5500B
                                 06631, Intel, Core i5,3550S
                                                                   09969, Intel, Core i7,4770
02434,AMD,A8,5545M
                                 06993, Intel, Core i5, 3570
                                                                   10190, Intel, Core i7, 4770K
03052, AMD, A8, 5550M
                                 07118, Intel, Core i5,3570K
                                                                   09803, Intel, Core i7,4770S
02935,AMD,A8,5557M
                                 06709, Intel, Core i5,3570S
                                                                   08803, Intel, Core i7,4770T
04348,AMD,A8,5600K
                                 05414, Intel, Core i5, 3570T
                                                                   10078, Intel, Core i7,4771
                                 04333, Intel, Core i5, 4200M
                                                                   08567, Intel, Core i7, 4800MQ
04390,AMD,A8,6500
                                                                   09969, Intel, Core i7,4820K
04719,AMD,A8,6600K
                                 03355, Intel, Core i5,4200U
                                                                   09331, Intel, Core i7, 4850HQ
04055, AMD, FX, 4100
                                 02358, Intel, Core i5, 4200Y
04153, AMD, FX, 4130
                                 02382, Intel, Core i5,4210Y
                                                                   09323, Intel, Core i7, 4900MQ
04094, AMD, FX, 4150
                                 03482, Intel, Core i5,4250U
                                                                   13620, Intel, Core i7,4930K
04774,AMD,FX,4170
                                 04381, Intel, Core i5, 4258U
                                                                   09754, Intel, Core i7, 4930MX
04711,AMD,FX,4300
                                 04663, Intel, Core i5,4288U
                                                                   10262, Intel, Core i7, 4960HQ
05247, AMD, FX, 4350
                                 04786, Intel, Core i5, 4300M
```

9.6.2. Program

Here is the program that will be producing the report. Pay attention to how the data is sorted and how the control hierarchy (CONTROLS ARE) relates to the SORT.

```
IDENTIFICATION DIVISION.
PROGRAM-ID. DEMORWCS.
ENVIRONMENT DIVISION.
CONFIGURATION SECTION.
REPOSITORY. FUNCTION ALL INTRINSIC.
INPUT-OUTPUT SECTION.
FILE-CONTROL.
    SELECT CPU-FILE
                                 ASSIGN TO "CPUDATA.txt"
                                 LINE SEQUENTIAL.
    SELECT REPORT-FILE
                                 ASSIGN TO "CPUREPORT.txt"
                                 LINE SEQUENTIAL.
    SELECT SORT-FILE
                                ASSIGN TO DISK.
DATA DIVISION.
FILE SECTION.
FD CPU-FILE.
                                PIC X(26).
01 CPU-REC
FD
  REPORT-FILE
```

```
REPORT IS CPU-Report.
SD SORT-FILE.
01 SORT-REC.

      05 F-SR-Score-NUM
      PIC 9(5).

      05 F-SR-Vendor-TXT
      PIC X(5).

      05 F-SR-Family-TXT
      PIC X(7).

      05 F-SR-Model-TXT
      PIC X(6).

WORKING-STORAGE SECTION.
01 WS-Date
                                   PIC 9(8).
01 WS-Family-Counters.
    05 WS-FC-AVE
                                   PIC 9(5) V99.
    05 WS-FC-Qty
                                 BINARY-LONG.
    05 WS-FC-Total-NUM BINARY-LONG.
01 WS-Flags.
    05 WS-F-EOF
                                    PIC X(1).
01 WS-One-Const
                                    PIC 9 VALUE 1.
01 WS-Overall-Counters.
    05 WS-OC-AVE
                                   PIC 9(5) V99.
    05 WS-OC-Qty
                                   BINARY-LONG.
    05 WS-OC-Total-NUM BINARY-LONG.
01 WS-Starz
                                    PIC X(44) VALUE ALL '*'.
01 WS-Vendor-Counters.
    05 WS-VC-AVE
                                   PIC 9(5) V99.
                                 BINARY-LONG.
    05 WS-VC-Qty
    05 WS-VC-Total-NUM BINARY-LONG.
REPORT SECTION.
RD CPU-Report
    CONTROLS ARE FINAL
                   F-SR-Vendor-TXT
                   F-SR-Family-TXT
    PAGE LIMIT IS
                       36 LINES
         HEADING
         FIRST DETAIL 5
         LAST DETAIL 36.
01 TYPE IS PAGE HEADING.
    05 LINE NUMBER PLUS 1.
        10 COL 1 SOURCE WS-Date
                                                    PIC 9999/99/99.
        10 COL 14 VALUE 'CPU Benchmark Scores'.
        10 COL 37 VALUE 'Page:'.
        10 COL 43 SOURCE PAGE-COUNTER
                                                   PIC Z9.
    05 LINE NUMBER PLUS 1.
```

```
10 COL 1 SOURCE WS-Starz
                                            PIC X(44).
   05 LINE NUMBER PLUS 1.
      10 COL 1 VALUE '**'.
       10 COL 6 VALUE 'All CPU Data From cpubenchmark.net'.
      10 COL 43 VALUE '**'.
   05 LINE NUMBER PLUS 1.
      10 COL 1 SOURCE WS-Starz
                                            PIC X(44).
01 TYPE CONTROL HEADING F-SR-Family-TXT.
   05 LINE NUMBER PLUS 1.
      10 COL 1 SOURCE F-SR-Vendor-TXT
                                           PIC X(6).
      10 COL 8 SOURCE F-SR-Family-TXT
                                            PIC X(7).
   05 LINE NUMBER PLUS 1.
      10 COL 1 VALUE 'Family'.
       10 COL 9 VALUE 'Model'.
      10 COL 16 VALUE 'Benchmark Score (High to Low)'.
   05 LINE NUMBER PLUS 1.
      10 COL 1 VALUE '====='.
      10 COL 9 VALUE '====='.
       10 COL 16 VALUE '========,'.
01 Detail-Line TYPE IS DETAIL.
   05 LINE NUMBER PLUS 1.
       10 COL 1 SOURCE F-SR-Family-TXT PIC X(7) GROUP INDICATE.
      10 COL 9 PIC X(6) SOURCE F-SR-Model-TXT.
      10 COL 16 PIC ZZZZ9 SOURCE F-SR-Score-NUM.
01 End-Family TYPE IS CONTROL FOOTING F-SR-Family-TXT.
   05 LINE NUMBER PLUS 1.
      10 COL 9
                              VALUE 'Ave...'.
      10 COL 16 PIC ZZZZ9.99 SOURCE WS-FC-AVE.
      10 COL 25 VALUE '('.
10 COL 26 PIC ZZ9 SUM WS-On
                                      WS-One-Const.
      10 COL 30
                               VALUE 'Family CPUs)'.
01 End-Vendor TYPE IS CONTROL FOOTING F-SR-Vendor-TXT.
   05 LINE NUMBER PLUS 1.
                               VALUE 'Ave...'.
      10 COL 9
      10 COL 16 PIC ZZZZ9.99 SOURCE WS-VC-AVE.
      10 COL 30
                               VALUE 'Vendor CPUs)'.
01 End-Overall TYPE IS CONTROL FOOTING FINAL.
   05 LINE NUMBER PLUS 1.
      10 COL 9
                               VALUE 'Ave...'.
      10 COL 16 PIC ZZZZ9.99 SOURCE WS-OC-AVE.
10 COL 25 VALUE '('.
10 COL 26 PIC ZZ9 SUM WS-One-Const.
10 COL 30 VALUE 'CPUs)'.
```

```
PROCEDURE DIVISION.
DECLARATIVES.
000-End-Family SECTION.
    USE BEFORE REPORTING End-Family.
1. IF WS-FC-Qty > 0
       COMPUTE WS-FC-AVE = WS-FC-Total-NUM / WS-FC-Qty
    ELSE
       MOVE O TO WS-FC-AVE
    END-IF
    MOVE O TO WS-FC-Qty
            WS-FC-Total-NUM
000-End-Vendor SECTION.
    USE BEFORE REPORTING End-Vendor.
1. IF WS-VC-Qty > 0
        COMPUTE WS-VC-AVE = WS-VC-Total-NUM / WS-VC-Qty
    ELSE
       MOVE O TO WS-VC-AVE
    END-IF
    MOVE O TO WS-VC-Qty
             WS-VC-Total-NUM
000-End-Overall SECTION.
    USE BEFORE REPORTING End-Overall.
1. IF WS-OC-Qty > 0
        COMPUTE WS-OC-AVE = WS-OC-Total-NUM / WS-OC-Qty
    ELSE
       MOVE O TO WS-OC-AVE
    END-IF
    MOVE O TO WS-OC-Qty
             WS-OC-Total-NUM
END DECLARATIVES.
010-Main SECTION.
1. ACCEPT WS-Date FROM DATE YYYYMMDD
    SORT SORT-FILE
        ASCENDING KEY F-SR-Vendor-TXT
                        F-SR-Family-TXT
        DESCENDING KEY F-SR-Score-NUM
        ASCENDING KEY F-SR-Model-TXT
        INPUT PROCEDURE 100-Pre-Process-Data
        OUTPUT PROCEDURE 200-Generate-Report
    STOP RUN
100-Pre-Process-Data SECTION.
1. OPEN INPUT CPU-FILE
    PERFORM FOREVER
       READ CPU-FILE
        AT END
           EXIT PERFORM
```

```
END-READ
        MOVE SPACES TO SORT-REC
        UNSTRING CPU-REC DELIMITED BY ','
            INTO F-SR-Score-NUM,
                 F-SR-Vendor-TXT,
                 F-SR-Family-TXT,
                 F-SR-Model-TXT
        RELEASE SORT-REC
    END-PERFORM
    CLOSE CPU-FILE
200-Generate-Report SECTION.
1. INITIALIZE WS-Family-Counters
              WS-Flags
    OPEN OUTPUT REPORT-FILE
    INITIATE CPU-Report
    RETURN SORT-FILE
    AT END
        MOVE 'Y' TO WS-F-EOF
    END-RETURN
    PERFORM UNTIL WS-F-EOF = 'Y'
        GENERATE Detail-Line
        ADD 1
                           TO WS-FC-Qty
                              WS-OC-Qty
                              WS-VC-Qty
        ADD F-SR-Score-NUM TO WS-FC-Total-NUM
                              WS-OC-Total-NUM
                              WS-VC-Total-NUM
        RETURN SORT-FILE
        AT END
            MOVE 'Y' TO WS-F-EOF
        END-RETURN
    END-PERFORM
    TERMINATE CPU-Report
    CLOSE REPORT-FILE
```

9.6.3. Generated Report Pages

Finally, here's the report the program generates!

```
5700
             4251
      4657M
             3449
      5750M
            3332
      5757M
             3253
      4600M
            3145
            2758
      5745M
      4655M
            2505
      Ave... 3817.90 ( 11 Family CPUs)
AMD
     Α4
Family Model Benchmark Score (High to Low)
_____
Α4
      6300
             2305
      5300
            2078
      5150M 1973
      5000
            1919
      3420
            1768
      4300M
            1685
      5300B
            1632
      3400
            1625
      3300
            1583
      3330MX 1343
      3310MX 1263
      3300M
            1237
      3305M
            1227
      3320M
            1193
2013/12/24 CPU Benchmark Scores Page: 2
*************
   All CPU Data From cpubenchmark.net
************
A4
      4355M 1169
      1200 677
      1250
             559
      Ave... 1484.47 ( 17 Family CPUs)
AMD
Family Model Benchmark Score (High to Low)
A6
      3670
            3327
      3650
            3232
      3620
            2892
      3600
            2798
      5200
            2440
      6400K
            2384
      3430MX 2277
      5400K
            2174
      3410MX 2101
      3420M
            2078
      3500
            1995
      3400M
            1964
      5350M
            1958
```

```
5400B
             1906
      5357M
             1878
      1450
             1634
      4400M
             1630
      4455M 1296
      Ave... 2220.22 ( 18 Family CPUs)
AMD
     8A
Family Model Benchmark Score (High to Low)
      6600K 4719
8A
      6500
             4390
      5600K
             4348
2013/12/24 CPU Benchmark Scores Page: 3
*************
    All CPU Data From cpubenchmark.net **
*************
      5500
             4052
8A
      3870K
             3682
      3850
             3552
      5500B
             3464
      3820
             3217
      3800
             3215
      5550M
             3052
      5557M
             2935
      3550MX 2866
      4500M
             2709
             2434
      5545M
      3510MX 2426
      3530MX 2276
      3520M
             2245
      4555M
             2193
      3500M 2050
      Ave... 3148.68 ( 19 Family CPUs)
AMD
Family Model Benchmark Score (High to Low)
10479
FΧ
      9590
      9370
           9807
      8350
             9067
      8320
             8131
      8150
             7719
      6350
             7017
      8140
             6845
      8120
             6605
      6300
             6388
      6200
             6194
      8100
             6163
      6120
             5813
```

```
2013/12/24 CPU Benchmark Scores
                           Page: 4
************
** All CPU Data From cpubenchmark.net **
************
FΧ
     6100
           5421
      4350
          5247
      4170
           4774
      4300 4711
          4153
      4130
      4150
           4094
      4100 4055
      Ave... 6457.00 ( 19 Family CPUs)
     Ave... 3448.86 (84 Vendor CPUs)
Intel Core i3
Family Model Benchmark Score (High to Low)
_____
Core i3 4340
           5117
      4330 5115
      4130 4904
      3250
          4757
          4414
      3245
      3225
          4407
           4259
      3240
      3220
           4219
      4130T
          4041
      3210
            3820
      3240T
            3793
      3220T
           3724
      3130M
           3655
      4000M
           3443
      3120M
           3301
           3076
      3110M
      3227U
           2575
      4010U 2459
      3217U
            2266
      4010Y
           2003
2013/12/24 CPU Benchmark Scores Page: 5
**************
   All CPU Data From cpubenchmark.net **
*************
Core i3 3229Y 1885
     Ave... 3677.76 ( 21 Family CPUs)
Intel Core i5
Family Model Benchmark Score (High to Low)
_____
Core i5 4670K 7565
     4670 7492
      3570K 7118
      4570 7061
```

```
3570
               6993
       3550
               6828
       4570S
               6803
       3570S
               6709
       3550S
               6631
       3470
               6576
       4440
               6517
       4570R
               6474
               6442
       3450
       4670T
               6351
       3340
               6282
       4430
               6282
       3350P
               6199
       3470S
               6077
       3450S
               6071
       3475S
               5991
       4430S
               5954
       3330
               5902
       3335S
               5781
               5690
       3330S
       3570T
               5414
       3340S
               5372
       4330M
               4804
2013/12/24 CPU Benchmark Scores Page: 6
**************
    All CPU Data From cpubenchmark.net
************
Core i5 4300M
               4786
       4288U
               4663
       3470T
               4591
       3380M
               4555
       4258U
               4381
       4200M
               4333
       3340M
               4327
       3360M
               4314
       3320M
               4101
       3230M
               3995
       4300U
               3917
       3210M
               3807
       4350U
               3604
       3427U
               3589
       4250U
               3482
       3437U
               3479
       4200U
               3355
       3337U
               3280
       3317U
               3126
       3439Y
               3057
       4570T
               2503
       4210Y
               2382
```

```
4200Y
             2358
      3339Y 2252
      4300Y 1743
      Ave... 5026.13 ( 52 Family CPUs)
Intel Core i7
Family Model Benchmark Score (High to Low)
_____
Core i7 4960X 14291
      4930K 13620
      3970X 12823
2013/12/24 CPU Benchmark Scores Page: 7
**************
   All CPU Data From cpubenchmark.net **
*************
Core i7 3960X 12718
      3930K 12107
      4960HQ 10262
      4770K 10190
      4771
            10078
      4770
             9969
      4820K 9969
      4770S
             9803
      4930MX 9754
      3770K
             9578
      3770
             9420
      4850HQ 9331
      4900MQ 9323
      3920XM 9196
      3770S
             9074
      3940XM 9052
      3840QM 9025
      3820
             8995
      4770T
             8803
      4800MQ 8567
      3820QM 8548
      3740QM 8512
      3720QM 8347
      3770T
             8280
      4700HQ 8161
      4750HQ 8066
      4702HQ
             8002
      4700MQ
             7946
      3630QM
             7759
      4702MQ
             7647
      3610QM 7532
      4765T
             7367
```

2013/12/24 CPU Benchmark Scores Page: 8

```
**************
    All CPU Data From cpubenchmark.net
*************
Core i7 4700EQ 7352
       3615QM
             7310
       3632QM 7055
       3612QE 6988
       3612QM 6907
       3635QM
             6516
       3610QE
             6144
       3615QE
             5495
       4600M
              4892
       3540M
              4861
       3520M
              4588
       4558U
              4507
       4600U
              4484
       4650U
              4345
       3687U
              4271
       3667U
              4032
       3555LE 4009
       4500U
              3992
       3537U
              3912
       3517U
              3701
       4610Y
              3680
       3689Y
              3479
       3517UE 3449
       Ave... 7725.58 ( 58 Family CPUs)
       Ave... 6005.16 (131 Vendor CPUs)
       Ave... 5006.42 (215 CPUs)
```

9.7. Control Hierarchy (Revisited)

The sample program just discussed presents a great opportunity to show what can happen if you don't define the control hierarchy of a report properly.

I changed the CONTROLS ARE clause on the sample program from this:

```
CONTROLS ARE FINAL F-SR-Vendor-TXT F-SR-Family-TXT
```

To this:

```
CONTROLS ARE FINAL F-SR-Family-TXT F-SR-Vendor-TXT
```

And then ran the report again. Here are the first two pages of that new report. See what happened to the control breaks?

```
2013/12/24 CPU Benchmark Scores
                            Page:
*************
** All CPU Data From cpubenchmark.net
*************
AMD
Family Model Benchmark Score (High to Low)
_____
A10
      6800K
            5062
      5800B 4798
      6700
            4767
      5800K
            4677
      5700
            4251
      4657M
            3449
      5750M
            3332
      5757M
            3253
      4600M
            3145
      5745M
            2758
      4655M 2505
      Ave... 3817.90 ( 11 Vendor CPUs)
      Ave... 3817.90 ( 11 Family CPUs)
AMD
     Α4
Family Model Benchmark Score (High to Low)
      _____
Α4
      6300
            2305
      5300
            2078
      5150M 1973
      5000
            1919
      3420
            1768
      4300M
            1685
      5300B
            1632
      3400
            1625
      3300
            1583
      3330MX 1343
      3310MX 1263
      3300M 1237
      3305M
            1227
2013/12/24 CPU Benchmark Scores Page: 2
**************
   All CPU Data From cpubenchmark.net
************
Α4
      3320M
           1193
      4355M 1169
      1200
            677
      1250
            559
      Ave... 1484.47 ( 17 Vendor CPUs)
```

| | Ave | 1484.47 (17 Family CPUs) |
|--------|--------|-------------------------------|
| AMD | A6 | |
| Family | Model | Benchmark Score (High to Low) |
| ===== | ===== | |
| A6 | 3670 | 3327 |
| | 3650 | 3232 |
| | 3620 | 2892 |
| | 3600 | 2798 |
| | 5200 | 2440 |
| | 6400K | 2384 |
| | 3430MX | 2277 |
| | 5400K | 2174 |
| | 3410MX | 2101 |
| | 3420M | 2078 |
| | 3500 | 1995 |
| | 3400M | 1964 |
| | 5350M | 1958 |
| | 5400B | 1906 |
| | 5357M | 1878 |
| | 1450 | 1634 |
| | 4400M | 1630 |
| | 4455M | 1296 |
| | Ave | 2220.22 (18 Vendor CPUs) |
| | Ave | 2220.22 (18 Family CPUs) |
| AMD | A8 | |
| - | | Benchmark Score (High to Low) |
| | ===== | |
| A8 | 6600K | 4/19 |

9.8. Turning PHYSICAL Page Formatting Into LOGICAL Formatting

You can trick RWCS into using the PAGE LIMIT values as logical specifications rather than physical ones quite easily — simply include an ASCII form-feed (X'OC') character into your page heading design! Here's how the sample program shown earlier could be easily modified:

Simply Change This...

```
O1 TYPE IS PAGE HEADING.

O5 LINE NUMBER 1.

10 COL 1 SOURCE WS-Date PIC 9999/99/99.

10 COL 14 VALUE 'CPU Benchmark Scores'.

10 COL 37 VALUE 'Page:'.

10 COL 43 SOURCE PAGE-COUNTER PIC Z9.

O5 LINE NUMBER PLUS 1.

10 COL 1 SOURCE WS-Starz PIC X(44).

O5 LINE NUMBER PLUS 1.

10 COL 1 VALUE '**'.

10 COL 6 VALUE 'All CPU Data From ' & 'cpubenchmark.net'.

10 COL 43 VALUE '**'.
```

```
05 LINE NUMBER PLUS 1.
            10 COL 1 SOURCE WS-Starz PIC X(44).
To This...
    01
        TYPE IS PAGE HEADING.
       05 LINE NUMBER 1.
                                           *> NEW
         10 COL 1 VALUE X'0C'.
                                          *> NEW
       05 LINE NUMBER PLUS 1.
                                          *> CHANGED
            10 COL 1 SOURCE WS-Date PIC 9999/99/99.
            10 COL 14 VALUE 'CPU Benchmark Scores'.
            10 COL 37 VALUE 'Page:'.
            10 COL 43 SOURCE PAGE-COUNTER PIC Z9.
         05 LINE NUMBER PLUS 1.
            10 COL 1 SOURCE WS-Starz PIC X(44).
         05 LINE NUMBER PLUS 1.
            10 COL 1 VALUE '**'.
            10 COL 6 VALUE 'All CPU Data From ' &
                            'cpubenchmark.net'.
            10 COL 43 VALUE '**'.
         05 LINE NUMBER PLUS 1.
            10 COL 1 SOURCE WS-Starz PIC X(44).
```

RWCS will still be counting lines to decide when to close off one page and start a new one, but when a new page is started its page heading will *physically* form-feed the printer when the report is printed. As long as any printer you plan on using supports at least as many physical print lines as what is defined as the PAGE LIMIT value in whatever paper orientation and font you plan on (or are limited to) printing in, you have now divorced your program from the physical realities of the printer!

Of course, whatever software you are using to deliver the printed document to the printer with, must allow the ASCII form-feed character to pass through to the printer.

End of Chapter 9 — Report Writer Usage

10. Interfacing With The OS

10.1. Compiling Programs

Program source files should have extensions of .cob or .cbl.

Program file names should match exactly the specification of PROGRAM-ID (including case).

Spaces cannot be included in primary entry-point names and therefore should not be included in program file names.

The GnuCOBOL compiler will translate your COBOL program into C source code, compile that C source code into executable binary form using the C compiler specified when GnuCOBOL was built and link that executable binary into:

Directly executable form

This is an executable file directly-executable from the command-line. On Windows computers, this would be an .exe file. On Unix systems, this will be a file with no specific extension, but with execute permissions. This file will include the main program as well as any static-linked subprograms.

Static-linkable form

This is a single subprogram compiled into object-code form, ready to be linked in with a main program to form a directly-executable program. On windows computers, these generally are .o (object-code) files.

Dynamically-loadable executable form

These are dynamically-loadable object code files ready to be invoked from other programs at execution time. On Windows systems, these would be .dll files, while on Unix systems they are typically .so files (OSX uses .dylib).

10.1.1. cobc - The GnuCOBOL Compiler

The GnuCOBOL compiler is named cobc (cobc.exe on a Windows system).

The following describes the syntax and option switches of the cobc command. This information may be displayed by entering the command cobc --help or cobc -h.

 ${\tt GnuCOBOL}$ compiler for most COBOL dialects with lots of extensions as of v3.1.

Usage: cobc [options]... file...

Options:

| -h, -help | display this help and exit |
|------------------|--|
| -V, -version | display compiler version and exit |
| -i, -info | display compiler information (build/environment) |
| | and exit |
| -v, -verbose | display compiler version and the commands |
| | invoked by the compiler |
| -vv, -verbose=2 | like -v but additional pass verbose option |
| | to assembler/compiler |
| -vvv, -verbose=3 | like -vv but additional pass verbose option |
| | to linker |
| -q, -brief | reduced displays, commands invoked not shown |
| -### | like -v but commands not executed |
| -x | build an executable program |
| | |

```
build a dynamically loadable module (default)
  -j [<args>], -job[=<args>]
                               run program after build, passing <args>
  -std=<dialect>
                         warnings/features for a specific dialect
                         <dialect> can be one of:
                         default, cobol2014, cobol2002, cobol85, xopen,
                         ibm-strict, ibm, mvs-strict, mvs,
                         mf-strict, mf, bs2000-strict, bs2000,
                         acu-strict, acu, rm-strict, rm;
                         see configuration files in directory config
 -F, -free
                         use free source format
  -fixed
                         use fixed source format (default)
  -0, -02, -03, -0s
                         enable optimization
  -00
                         disable optimization
                         enable C compiler debug / stack check / trace
  -g
  -d, -debug
                         enable all run-time error checking
  -o <file>
                         place the output into <file>
  -b
                         combine all input files into a single
                         dynamically loadable module
  -E
                         preprocess only; do not compile or link
                         translation only; convert COBOL to C
  -C
  -S
                         compile only; output assembly file
                         compile and assemble, but do not link
  -с
                         generate and place a wide program listing into <file>
 -T <file>
                         generate and place a program listing into <file>
  -t <file>
                         specify lines per page in listing, default = 55
  --tlines=<lines>
                         generate preprocessed program listing (.lst)
  -P[=<dir or file>]
  -Xref
                         generate cross reference through 'cobxref'
                         (V. Coen's 'cobxref' must be in path)
                         {This uses the internal tool only. See 10.1.1.1 for example
                         output.
                         To use Cobxref you must run this separately.
                         See second example as 10.1.1.2}
 -I <directory>
                         add <directory> to copy/include search path
 -L <directory>
                         add <directory> to library search path
 -l <lib>
                         link the library <lib>
 -A <options>
                         add <options> to the C compile phase
                         add <options> to the C link phase
  -Q <options>
  -D <define>
                        define <define> for COBOL compilation
  -K <entry>
                        generate CALL to <entry> as static
  -conf=<file>
                         user-defined dialect configuration; see -std
  -list-reserved
                         display reserved words
  -list-intrinsics
                         display intrinsic functions
  -list-mnemonics
                         display mnemonic names
                         display system routines
  -list-system
  -save-temps[=<dir>]
                         save intermediate files
                         * default: current directory
 -ext <extension>
                         add file extension for resolving COPY
Warning options:
```

enable all warnings

-W

-Wall enable most warnings (all except as noted below) warn if archaic features are used -Warchaic -Warithmetic-osvs warn if arithmetic expression precision has changed warn about non 01/77 items for CALL parameters -Wcall-params \* NOT set with -Wall -Wcolumn-overflow warn about text after program-text area, FIXED format \* NOT set with -Wall -Wconstant-expression warn about expressions that always resolve to true/false warn about CORRESPONDING with no matching items -Wcorresponding -Werror treat all warnings as errors
-Werror=<warning> treat specified <warning> as error
-Wimplicit-define warn about implicitly defined data items
-Winitial-value warn if initial VALUE clause is ignored
-Wlinkage warn about dargling ITW/CD \* NOT set with -Wall disable warning enabled by -W or -Wall -Wno-<warning> -Wno-dialect do not warn about dialect specific issues \* ALWAYS active do not warn if pending features are mentioned -Wno-pending \* ALWAYS active -Wno-unfinished do not warn if unfinished features are used \* ALWAYS active -Wobsolete warn if obsolete features are used -Wothers do not warn about different issues \* ALWAYS active -Woverlap warn about overlapping MOVE of items -Woverlap warn about overlapping MOVE of items
-Wparentheses warn about lack of parentheses around AND within OR
-Wpossible-overlap warn about MOVE of items that may overlap depending on variables \* NOT set with -Wall -Wpossible-truncate warn about possible field truncation \* NOT set with -Wall warn about missing FUNCTION prototypes/definitions -Wprototypes -Wredefinition warn about incompatible redefinition of data items -Wstrict-typing warn strictly about type mismatch -Wterminator warn about lack of scope terminator END-XXX \* NOT set with -Wall warn about field truncation from constant assignments -Wtruncate warn about likely unreachable statements -Wunreachable \* NOT set with -Wall Compiler options: -facucomment '\$' in indicator area treated as '\*', '|' treated as floating comment -fcallfh=<function> use external provided EXTFH interface module <function> for I/O -fdebugging-line enable debugging lines \* 'D' in indicator column or floating >>D -fdefaultbyte=<value> initialize fields without VALUE to value \* decimal 0..255 or any quoted character \* default: initialize to picture

```
-fdump=<scope>
                       dump data fields on abort, <scope> may be
                       a combination of: ALL, WS, LS, RD, FD, SC
-ffold-call=[UPPER|LOWER]
                       fold PROGRAM-ID, CALL, CANCEL subject to value
                       * default: no transformation
-ffold-copy=[UPPER|LOWER]
                      fold COPY subject to value
                       * default: no transformation
                       sets -fbinary-size=2-4-8 -fsynchronized-clause=ok
-fibmcomp
-fimplicit-init
                       automatic initialization of the COBOL runtime system
-finline-intrinsic
                     whe n possible resolve intrinsic FUNCTIONs at compile time
-fintrinsics=[ALL|intr insic function name(,name,...)]
                       intrinsics to be used without FUNCTION keyword
-fmax-errors=<number> maximum number of errors to report before
                       compilation is aborted
                       * default: 100
-fmf-files
                       Sequential & Relative files will match Micro Focus format
                       '*' or '/' in column 1 treated as comment
-fmfcomment
                       * FIXED format only
-fno-gen-c-decl-static -call disable generation of C function declarations
                       for subroutines with static CALL
                       sets -fbinary-size=1--8 -fsynchronized-clause=ignore
-fno-ibmcomp
                      disable check of recursive program call;
-fno-recursive-check
                       effectively compiling as RECURSIVE program
                              disable remove of unreachable code
-fno-remove-unreachabl e
                       * turned off by -g
                       suppress all headers and output of compilation
-fno-theaders
                       options from listing while keeping page breaks
                       suppress warning and error summary from listing
-fno-tmessages
-fno-tsource
                       suppress source from listing
                       allow numeric field overflow
-fnotrunc
                       * non-ANSI behaviour
-fodoslide
                       adjust items following OCCURS DEPENDING
                       * implies -fcomplex-odo
                      treat all files as OPTIONAL
-foptional-file
                       * unless NOT OPTIONAL specified
-fsign=[ASCII|EBCDIC] define display sign representation
                       * default: machine native
-fsingle-quote
                       use a single quote (apostrophe) for QUOTE
                       * default: double quote
-fsource-location
                       generate source location code
                       * turned on by -debug/-g/-ftraceall
-fstack-check
                       PERFORM stack checking
                       * turned on by -debug or -g
-fstatic-call
                       output static function calls for the CALL statement
-fsyntax-only
                       syntax error checking only; don't emit any output
-ftrace
                       generate trace code
                       * scope: executed SECTION/PARAGRAPH
-ftraceall
                       generate trace code
                       * scope: executed SECTION/PARAGRAPH/STATEMENTS
                       * turned on by -debug
```

-ftsymbols specify symbols in listing

-fwrite-after use AFTER 1 for WRITE of LINE SEQUENTIAL

\* default: BEFORE 1

Compiler dialect configuration options:

-faccept-auto Set WITH AUTO clause as default for ACCEPT dest-item,

instead of WITH TAB

-faccept-display-extensions=<support>

Extensions to ACCEPT and DISPLAY

-faccept-update Set WITH UPDATE clause as default for ACCEPT dest-item,

instead of WITH NO UPDATE

-facu-literals=<support>

ACUCOBOL-GT literals (#B #0 #H #X)

-falter-statement=<support>

ALTER statement

-farithmetic-osvs Limit precision in intermediate results to precision

of final result (less accurate)

-fassign-clause=<value>

Set way of interpreting ASSIGN

-fbinary-byteorder=<value>

Binary byte order, may be one of: native, big-endian

-fbinary-comp-1 COMP-1 is a 16-bit signed integer

-fbinary-size=<value> Binary byte size - defines the allocated bytes according

to PIC, may be one of: 2-4-8, 1-2-4-8, 1--8

-fbinary-sync-clause=<support>

BINARY-SHORT/LONG/DOUBLE SYNCHRONIZED clause

-fbinary-truncate Numeric truncation according to ANSI

-fcall-convention-linkage=<support>

Specifying call-convention by WITH ... LINKAGE

-fcall-convention-mnemonic=<support>

Specifying call-convention by mnemonic

-fcall-overflow=<support>

OVERFLOW clause for CALL

-fcomment-paragraphs=<support>

Comment paragraphs in IDENTIFICATION DIVISION (AUTHOR,

DATE-WRITTEN, ...)

-fcomplex-odo Allow complex OCCURS DEPENDING ON

-fconsole-is-crt Assume CONSOLE IS CRT if not set otherwise

-fconstant-01=<support>

Constant with level 01 CONSTANT AS/FROM item

-fconstant-78=<support>

Constant with level 78 item (note: has left to right

precedence in expressions)

-fconstant-folding Evaluate constant expressions at compile time

-fcontinue-after=<support>

AFTER phrase in CONTINUE statement

-fdata-records-clause=<support>

DATA-RECORDS clause

-fdebugging-mode=<support>

DEBUGGING MODE and debugging indicator

-fdefine-constant-directive=<support>

```
Allow >> DEFINE CONSTANT var AS literal
-fdepending-on-not-fixed=<support>
                        Depending-on-not-fixed
-fdisplay-special-fig-consts
                        Special behaviour of
                        DISPLAY SPACE/ALL X'01'/ALL X'02'/ALL X'07'
-fentry-statement=<support>
                        ENTRY statement
-ffilename-mapping
                        Resolve file names at run time using environment variables.
-ffree-redefines-position=<support>
                        REDEFINES clause not following entry-name in definition
-fgoto-entry=<support>
                        ENTRY FOR GOTO and GOTO ENTRY statements
-fgoto-statement-without-name=<support>
                        GOTO statement without name
-fhexadecimal-boolean=<support>
                        Hexadecimal-boolean literals (BX'A')
-fhexadecimal-national-literals=<support>
                        Hexadecimal-national literals (NX'265E')
                        Allow hexadecimal value 'F' for NUMERIC test of signed
-fhostsign
                        PACKED DECIMAL field
-fhp-octal-literals=<support>
                       HP COBOL octal literals (%377)
-fincorrect-conf-sec-order=<support>
                       Incorrect order of CONFIGURATION SECTION paragraphs
-findirect-redefines Allow REDEFINES to other than last equal level number
-flabel-records-clause=<support>
                        LABEL-RECORDS clause
-flarger-redefines-ok
                        Allow larger REDEFINES items
-flength-in-data-division
                        Length in data division
-fline-col-zero-default
                        Assume the first item in a field DISPLAY goes at
                        LINE O COL O, not LINE 1 COL 1
-flisting-statements=<support>
                        Listing-directive statements EJECT, SKIP1, SKIP2, SKIP3
-fliteral-length=<number>
                        Maximum literal size in general
-fmemory-size-clause=<support>
                        MEMORY-SIZE clause
-fmissing-statement=<support>
                        Missing statement (e.g. empty IF / PERFORM)
-fmove-figurative-constant-to-numeric=<support>
                        Move figurative constants to numeric
-fmove-figurative-quote-to-numeric=<support>
                        Move figurative constant QUOTE to numeric
-fmove-figurative-space-to-numeric=<support>
                        Move figurative constant SPACE to numeric
                        MOVE operates as on IBM (left to right, byte by byte),
-fmove-ibm
                        otherwise no propagating move
```

```
-fmove-non-numeric-lit-to-numeric-is-zero
                        Imply zero in move of non-numeric literal to numeric items
-fmove-noninteger-to-alphanumeric=<support>
                        Move noninteger to alphanumeric
-fmultiple-file-tape-clause=<support>
                       MULTIPLE-FILE-TAPE clause
-fnational-character-literals=<support>
                       Non-standard national literals (NC'UTF-16 string')
-fnational-literals=<support>
                        National literals (N'UTF-16 string')
-fnext-sentence-phrase=<support>
                       NEXT SENTENCE phrase
-fno-echo-means-secure
                       NO-ECHO
                        Hides input with asterisks like SECURE
-fnonnumeric-with-numeric-group-usage=<support>
                       Non-Numeric item with Numeric Group USAGE clause
-fnot-exception-before-exception=<support>
                        NOT ON EXCEPTION before ON EXCEPTION
-fnumeric-boolean=<support>
                        Boolean literals (B'1010')
-fnumeric-literal-length=1..38
                       Maximum numeric literal size
-fnumeric-value-for-edited-item=<support>
                       Numeric literals in VALUE clause of numeric-edited items
-foccurs-max-length-without-subscript
                        Occurs max length without subscript
-fodo-without-to=<support>
                        OCCURS DEPENDING ON without to
-fpadding-character-clause=<support>
                       PADDING CHARACTER clause
                        exit point of any currently executing perform is recognized
-fperform-osvs
                        if reached
-fperform-varying-without-by=<support>
                       PERFORM VARYING without BY phrase (implies BY 1)
-fpic-length=<number>
                       Maximum number of characters allowed in the PICTURE
                       character-string
-fpretty-display
                       Alternate formatting of numeric fields
-fprogram-name-redefinition
                       Program names don't lead to a reserved identifier
-fprogram-prototypes=<support>
                        CALL/CANCEL with program-prototype-name
-frecord-delim-with-fixed-recs=<support>
                        RECORD DELIMITER clause on file with fixed-length records
-frecord-delimiter=<support>
                        RECORD DELIMITER clause
-frecords-mismatch-record-clause=<support>
                        Record sizes does not match RECORD clause
-freference-out-of-declaratives=<support>
                        References to sections not in DECLARATIVES from within
```

DECLARATIVES

```
-frelax-level-hierarchy
                       Allow non-matching level numbers
-frelax-syntax-checks Allow certain syntax variations (e.g. REDEFINES position)
-frenames-uncommon-levels=<support>
                        RENAMES of 01-, 66- and 77-level items
-freserved-words=<value>
                       Use of complete/fixed reserved words
-fscreen-section-rules=<value>
                        Which compiler's rules to apply to SCREEN SECTION
                        item clauses
-fsection-segments=<support>
                        Section segments
-fselect-working
                       Require ASSIGN USING items to be in WORKING-STORAGE
-fsequential-delimiters=<support>
                        BINARY-SEQUENTIAL and LINE-SEQUENTIAL phrases in
                       RECORD DELIMITER
-fsticky-linkage
                       LINKAGE-SECTION items remain allocated between invocations
-fstop-identifier-statement=<support>
                        STOP-identifier statement
-fstop-literal-statement=<support>
                        STOP-literal statement
-fsymbolic-constant=<support>
                        Constants defined in SPECIAL-NAMES
-fsynchronized-clause=<support>
                       SYNCHRONIZED clause
-ftab-width=1..12
                       Set number of spaces that are assumed for tabs
-ftext-column=72..255 Set right margin for source (fixed format only)
-ftitle-statement=<support>
                        Listing-directive statement TITLE
-ftop-level-occurs-clause=<support>
                        OCCURS clause on top-level
-fuse-for-debugging=<support>
                        USE FOR DEBUGGING
-fvalue-of-clause=<support>
                        VALUE-OF clause
-fword-continuation=<support>
                        Continuation of COBOL words
                       Maximum word-length for COBOL (= programmer defined) words
-fword-length=1..63
-fxml-generate-extra-phrases=<support>
                        XML GENERATE's phrases other than COUNT IN
-fzero-length-literals=<support>
                        Zero-length literals, e.g. '@w{}' and ""
  where <support> is one of the following:
      'ok', 'warning', 'archaic', 'obsolete', 'skip', 'ignore', 'error',
    'unconformable'
-fnot-reserved=<word>
                        Word to be taken out of the reserved words list
-freserved=<word>
                       Word to be added to reserved words list
-freserved=<word>:<alias>
                        Word to be added to reserved words list as alias
                       Special register to disable
-fnot-register=<word>
```

-fregister=<word> Special register to enable

Each file specified on the cobc command constitutes a *Compilation Unit*. A compilation unit may be a single GnuCOBOL program — with or without nested subprograms(see [Independent vs Contained vs Nested Subprograms], page 603) — or multiple GnuCOBOL programs, separated by END PROGRAM or END FUNCTION marker lines, as appropriate. See [Independent vs Contained vs Nested Subprograms], page 603, for some examples of these marker lines.

A compilation unit may also be a C-language source program, recognized as such by having a file extension of .c or an assembly-language program, recognized by its file extension of .s. In such a case, *COBOL* compilation of that file will be bypassed by the cobc command; instead, the file will be passed directly to the C compiler or assembler (executed automatically by cobc).

A compilation unit may *also* be an object-code module (output from the C compiler), recognized as such by having a file extension of .o. In these situations, all compilation will be bypassed, and the object code will be "bound" into the generated executable by the linker (an ld command executed internally by the cobc command).

Pre-compiled object-code subprograms may be automatically located by the GnuCOBOL compiler and the loader by using the LD\_LIBRARY\_PATH compilation-time environment variable (see [Compilation Time Environment Variables], page 571). If they are locatable through that environment variable, they need not be named on the cobc command.

The collection of compilation units supplied on a *single* cobc execution constitute a *Compilation Group*. All executable code produced from a single compilation group will be collected together into a single executable file, whose filename will be the same as that of the first compilation unit specified on the cobc command.

The simplest mode of compilation is to generate a single executable file from one or more GnuCOBOL source files:

cobc -x mainprog.cbl sub1.cbl sub2.cbl

The main program must be the first program found in the first compilation unit (mainprog.cbl). The remainder of that compilation unit as well as the rest of the files in the compilation group (sub1.cbl and sub2.cbl) must be independent and/or contained subprograms (see [Independent vs Contained vs Nested Subprograms], page 603).

This command assumes that all source files are in the directory from which the cobc command was executed. You are, of course, free to include full pathnames with any filename, if necessary.

With the -x switch on the compiler command, a single directly-executable executable file (UNIX, Windows/Cygwin, OSX) or "exe" file (Windows, Windows/MinGW) will be generated. This executable file has the compiled code for all COBOL programs contained within the compilation group specified on the cobc command included in the file.

Any subroutines or user-defined functions that weren't included in any of the source files comprising the compilation group will be treated as dynamically loadable subprograms (see [Dynamic vs Static Subprograms], page 605).

Optionally, the -o switch may be used in addition to -x to specify the name of the generated executable file. If -o switch is not specified, the filename of the 1st compilation unit will be used as the name of the executable file. The appropriate extension for the generated file (.exe, on a Windows computer, for example) will be added to the filename that is explicitly specified or implicitly assumed for the output file.

Compilations may be performed to generate dynamically-loadable modules (or dynamically-loadable libraries, as they are frequently called). These compilations are performed by using the -m switch instead of -x switch:

cobc -m mainprog.cbl sub1.cbl sub2.cbl

When the -m switch is used, an operating-system-specific dynamically-loadable module is generated for each individual compilation unit, using the filename of each compilation unit as its module filename and either an extension of .so (UNIX, Windows/Cygwin), .dylib (OSX) or .dll (Windows, Windows/MinGW).

You may compile GnuCOBOL subprograms into assembler source code which can then be assembled and linked with a main program when that main program is compiled. To create such an assembler source file, compile the subprogram(s) as follows:

```
cobc -S sprog1.cbl
```

The above generates an assembler source file named sprog1.s. If you have multiple subprograms to compile this way, just string their file names out on the command. Each will be translated to its own assembler source file.

Later, when you wish to compile a calling program and combine any needed assembly language subroutines in (as static subroutines — see [Dynamic vs Static Subprograms], page 605), use a command such as this:

cobc -x mainprog.cbl sprog1.s

10.1.1.1. cobc option -Xref an example

The following shows the output from using -Xref.

Using the internal -Xref as extra options -X -t prog.list:

```
GnuCOBOL 3.1.2.0
                      prog.cbl
                                         Thu Nov 25 15:31:52 2021 Page 0001
LINE
       000001 000001 IDENTIFICATION
                             DIVISION.
000002 000002 PROGRAM-ID.
000003 000003 ENVIRONMENT DIVISION.
000004 000004 CONFIGURATION SECTION.
000005 000005 DATA
                             DIVISION.
000006 000006 WORKING-STORAGE SECTION.
000007 000007 COPY 'values.cpy'.
000001C 000001 78 I
                     VALUE 20.
                     VALUE 5000.
000002C 000002 78
                J
000003C 000003 78 M
                     VALUE 5.
000008 000008 01 SETUP-REC.
                              PIC X(04).
000009
      000009
                 05 FL1
000010 000010
                 05 FL2
                              PIC ZZZZZ.
000011 000011
                 05 FL3
                              PIC 9(04).
000012
      000012
                 05 FL4
                              PIC 9(08) COMP.
000013 000013
                 05 FL5
                              PIC 9(04) COMP-4.
000014 000014
                 05 FL6
                              PIC Z,ZZZ.99.
000015
      000015
                 05 FL7
                              PIC S9(05) SIGN LEADING SEPARATE.
000016 000016
                 05 FL8
                              PIC X(04).
000017
      000017
                 05 FL9 REDEFINES FL8 PIC 9(04).
000018
      000018
                 05 FLA.
                     10 FLB OCCURS I TIMES.
000019
       000019
       000020
                        15 FLC PIC X(02).
000020
000021
       000021
                     10 FLD
                              PIC X(20).
000022
                              PIC X(100).
      000022
                 05 FLD1
```

```
000023 000025 05 FLD3 PIC X(3).
000024 000026 05 FLD4 PIC X(4).
000025 000023 05 FLD2 OCCURS M TO J TIMES DEPENDING ON FL5.
000026 000024 10 FILLER PIC X(01).
000027 000027 PROCEDURE DIVISION.
000028 000028 STOP RUN.
```

GnuCOBOL 3.1.2.0 prog.cbl Thu Nov 25 15:31:52 2021 Page 0002

| NAME | DEFINE | ED REFERENCES | |
|-----------|--------|---------------------|----|
| SETUP-REC | 8 | referenced by child | |
| FL1 | 9 | not referenced | |
| FL2 | 10 | not referenced | |
| FL3 | 11 | not referenced | |
| FL4 | 12 | not referenced | |
| FL5 | 13 | 25 | x1 |
| FL6 | 14 | not referenced | |
| FL7 | 15 | not referenced | |
| FL8 | 16 | not referenced | |
| FL9 | 17 | not referenced | |
| FLA | 18 | not referenced | |
| FLB | 19 | not referenced | |
| FLC | 20 | not referenced | |
| FLD | 21 | not referenced | |
| FLD1 | 22 | not referenced | |
| FLD3 | 23 | not referenced | |
| FLD4 | 24 | not referenced | |
| FLD2 | 25 | not referenced | |

| GnuCOBOL 3.1.2.0 | prog.cbl | Thu Nov | 25 | 15:31:52 | 2021 | Page 0003 |
|------------------|----------|---------|----|----------|------|-----------|
| | | | | | | |

LABEL DEFINED REFERENCES

E prog 27

10.1.1.2. Cross Reference listing using cobxref

This program is found in the contrib area or by itself in Sourceforge under its own name (cobxref).

The following shows the output from using cobxref with the same program example.

Note that cobxref also reports the COPY depth which can be up to 9 and includes the program being compiled as depth 1.

Using cobxref with command cobxref prog.cbl:

ACS Cobol Xref v2.02.03 Dictionary File for PROG 25/11/2021 15:22:00:04 Page 1

 $<sup>{\</sup>tt 0}$ warnings in compilation group

O errors in compilation group

```
1 000001 IDENTIFICATION DIVISION.
       2 000002 PROGRAM-ID.
                                              prog.
          000003 ENVIRONMENT DIVISION.
       4 000004 CONFIGURATION SECTION.
       5 000005 DATA
                                   DIVISION.
       6 000006 WORKING-STORAGE SECTION.
           000007*COPY 'values.cpy'.
       7
          000001 78 I VALUE 20.
       9
          000002 78 J
                                 VALUE 5000.
      10 000003 78 M VALUE 5.
      11 000008 01 SETUP-REC.
     11 000008 01 SETUP-REC.

12 000009 05 FL1 PIC X(04).

13 000010 05 FL2 PIC ZZZZZ.

14 000011 05 FL3 PIC 9(04).

15 000012 05 FL4 PIC 9(08) COMP.

16 000013 05 FL5 PIC 9(04) COMP-4.

17 000014 05 FL6 PIC Z,ZZZ.99.

18 000015 05 FL7 PIC S9(05) SIGN LEADING SEPARATE.

19 000016 05 FL8 PIC X(04).

20 000017 05 FL9 REDEFINES FL8 PIC 9(04).

21 000018 05 FLA.

22 000019 10 FLB OCCURS I TIMES.
     22 000019 10 FLB OCCURS I TIMES.
23 000020 15 FLC PIC X(02).
24 000021 10 FLD PIC X(20).
25 000022 05 FLD1 PIC X(100).
26 000025 05 FLD3 PIC X(3).
27 000026 05 FLD4 PIC X(4).
     28 000023 05 FLD2 OCCURS M TO J TIMES DEPENDING ON FL5.
     29 000024
                                 10 FILLER PIC X(01).
      30 000027 PROCEDURE
                                          DIVISION.
     31 000028 STOP RUN.
      32
                    *>>>Info: Total Copy Depth Used = 02
ACS Cobol Xref v2.02.03
                                               Dictionary File for PROG 25/11/2021 15:22:00:04
                                                 Page
Symbols of Module: PROG (PROG)
Data Section (WORKING-STORAGE) Defn Locations
FL1
                                              000012W
FL2
                                              000013W
FL3
                                              000014W
FL4
                                              000015W
FL5
                                              000016W 000028
                                              000017W
FL6
FL7
                                              000018W
```

000019W 000020

FL8

| FL9 | 000020W | | | |
|--------------------------------|---------|-------------------|------------|-------------|
| FLA | 000021W | | | |
| FLB | 000022W | | | |
| FLC | 000023W | | | |
| FLD | 000024W | | | |
| FLD1 | 000025W | | | |
| FLD2 | 000028W | | | |
| FLD3 | 000026W | | | |
| FLD4 | 000027W | | | |
| I | W800000 | 000022 | | |
| J | 000009W | 000028 | | |
| M | 000010W | 000028 | | |
| SETUP-REC | 000011W | | | |
| ACS Cobol Xref v2.02.03 | Diction | ary File for PROG | 25/11/2021 | 15:22:00:04 |
| | Page | 3 | | |
| Symbols of Module: PROG (PROG) | _ | | | |
| Procedure | Defn | Locations | | |

None

10.1.2. Compilation Time Environment Variables

The following are the various environment variables that can play a role in the compilation of GnuCOBOL programs.

 ${\tt COB\_CC}~*~$ Set to the name of the C compiler you wish GnuCOBOL to use.

Use this feature at your own risk – you should always use the c compiler your gnucobol build was generated for.

COB\_CFLAGS \*

Set to any switches that you'd like to pass on to the C compiler from the cobc compiler (in addition to any that cobc will specify).

COB\_CONFIG\_DIR \*

Set to the path to the folder where GnuCOBOL config files are kept.

COB\_COPY\_DIR \*

If copybooks your program needs are *not* stored in the same directory as your program, set this environment variable to the folder in which the copybooks may be found (IBM mainframe programmers will recognize this as SYSLIB).

COB\_LDADD

Set to any additional linker switches (1d) that can specify where standard libraries that must be linked with the program can be found. The default is "" (empty).

COB\_LDFLAGS

Set to any linker (1d) switches that you'd like to pass on to the C compiler from the cobc compiler (in addition to any that cobc will specify).

COB\_LIBS \*

Set to any linker switches (1d) that specify where standard libraries that must be linked with the program can be found.

COBCPY This environment variable provides an additional means of specifying where copybooks may be found by the compiler (see also COB\_COPY\_DIR, above).

LD\_LIBRARY\_PATH

If you are planning on using static-linked subroutine libraries, set this variable to the path of the directory containing your libraries.

TMPDIR

TMP

Set to a directory/folder appropriate to create temporary files in. The intermediate working files created by the compiler will be created here (and deleted once they're no longer needed).

The variable TMPDIR is checked for a valid path first; if that isn't set, then TMP is checked.

On a Windows system, the TMP environment variable is normally set for you when you logon. If you wish to use a different temporary folder, you may set TMPDIR yourself and have no fear of disrupting other Windows software that relies on TMP.

\* The starred environment variables above have default values, established when the version of GnuCOBOL you are using was built. To see these default values, as well as other build-specific information, execute the command:

cobc -i

10.1.3. Predefined Compilation Variables

GnuCOBOL defines compilation variables when certain conditions are true.

If the condition associated with a variable is false, the variable is not defined during compilations.

DEBUG The -d debug flag is specified.

EXECUTABLE

The module being compiled contains the main program.

GCCOMP

The size of a COMP item is determined according to the GnuCOBOL scheme, where for a PICTURE of length:

1-2 item has 1 byte

3-4 item has 2 bytes

5-9 item has 4 bytes

10-18 item has 8 bytes.

GNUCOBOL GnuCOBOL is compiling the source unit.

HOSTSIGNS

A signed packed-decimal item's value may be considered NUMERIC if the sign has value X"F".

IBMCOMP The size of a COMP item is determined according to the IBM scheme, where for a PICTURE of length:

1-4 item has 2 bytes

5-9 item has 4 bytes

10-18 item has 8 bytes.

MODULE The module being compiled does not contain the main program.

NOHOSTSIGNS

A signed packed-decimal item's value may not be considered

NUMERIC if the sign has value X"F".

NOIBMCOMP

The size of a COMP item is not determined according to the IBM scheme.

NOSTICKYLINKAGE

Sticky-linkage (linkage-section items remaining allocated between invocations) is not enabled

NOTRUNC
Numeric data items are truncated according to their internal representation.

P64 Pointers are greater than 32 bits long

STICKY-LINKAGE

Sticky-linkage (linkage-section items remaining allocated between invocations) is enabled.

TRUNC Numeric data items are truncated according to their PICTURE clauses.

10.1.4. Locating Copybooks

The GnuCOBOL compiler will attempt to locate copybooks by searching for them in the following folders. The search will occur in the sequence shown below, and will terminate once a copybook is found.

- 1. The folder named as the *library-name-1* on the COPY statement (see [COPY], page 59).
- 2. The folder in which the program being compiled resides.
- 3. The folder named on the -I switch.
- 4. Each of the folders named on the COBCPY compilation-time environment variable (see [Compilation Time Environment Variables], page 571).

A single folder may be named or multiple folders may be specified, separated by a system-appropriate delimiter character. When multiple folders are specified, they will be searched in the order they are named on the environment variable.

If the GnuCOBOL compiler you are using was built to utilize a native Windows environment, use a semicolon (';') as the delimiter character.

If, however, the GnuCOBOL compiler was built for a Unix, OSX or Linux environment, or was built for a Windows environment utilizing either the Cygwin or MinGW Unix emulators, use a colon character (':') as the delimiter.

5. The single folder specified on the COB\_COPY\_DIR environment variable.

As each of the above folders is searched for a copybook — COPY XXXXXXXX., for example — the GnuCOBOL compiler will attempt to locate the copybook file by any of the following names, in the sequence shown:

```
XXXXXXXX.CPY
XXXXXXXX.COB
XXXXXXXXX.cpy
XXXXXXXXX.cbl
XXXXXXXX.cob
XXXXXXXX
```

The COPY statement is case-sensitive on UNIX systems; COPY copybookname and COPY COPYBOOKNAME will both fail to locate the CopyBookName copybook on a UNIX system.

Windows implementations of GnuCOBOL may, or may not, be similarly case sensitive with regard to copybook names, depending upon the Windows version and GnuCOBOL build options — it is safest to simply treat the COPY command as case-sensitive in all environments.

It is possible, however, to automatically cause all COPY statements to "fold" the names of all copybooks to upper-case by specifying the <code>-ffold-copy</code> switch with the upper option (i.e. <code>--fold-copy=upper</code>) to the GnuCOBOL compiler. Similarly, names could be folded to lower-case by using the <code>lower</code> option (i.e. <code>--fold-copy=lower</code>. If copybook libraries are maintained entirely using upper- or lower-case file names and extensions, either of these options will allow copybooks to be found regardless of how the programmer entered their names on COPY statements.

Case-folding may also be turned on and off within the program source code using the CDF >>SET statement (see [>>SET], page 66).

10.1.5. Compiler Configuration Files

GnuCOBOL uses compiler configuration files to define various options that will control the compilation process. These configuration files are specified using the <code>-conf</code> switch compilation

switch and are found in the folder defined by the COB\_CONFIG\_DIR compilation-time environment variable (see [Compilation Time Environment Variables], page 571).

If this is not defined under \*nix it will default to /usr/local/share/gnucobol/config.

The following is a verbatim listing of the default configuration file (the one used if you don't specify the <code>-conf</code> switch), just to show you the types of settings that may appear and taken from v3.1.2:

```
# GnuCOBOL compiler configuration
# Copyright (C) 2001-2012, 2014-2020 Free Software Foundation, Inc.
# Written by Keisuke Nishida, Roger While, Simon Sobisch, Edward Hart,
# Ron Norman
# This file is part of GnuCOBOL.
# The GnuCOBOL compiler is free software: you can redistribute it
# and/or modify it under the terms of the GNU General Public License
# as published by the Free Software Foundation, either version 3 of the
# License, or (at your option) any later version.
# GnuCOBOL is distributed in the hope that it will be useful,
# but WITHOUT ANY WARRANTY; without even the implied warranty of
# MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
# GNU General Public License for more details.
# You should have received a copy of the GNU General Public License
# along with GnuCOBOL. If not, see <a href="https://www.gnu.org/licenses/">https://www.gnu.org/licenses/</a>.
# Value: any string
name: "GnuCOBOL"
# Value: enum
standard-define
                                 0
         CB\_STD\_GC = 0,
#
         CB_STD_MF,
#
         CB_STD_IBM,
#
         CB_STD_MVS,
#
         CB_STD_BS2000,
#
         CB_STD_ACU,
#
         CB_STD_85,
#
         CB_STD_2002,
         CB_STD_2014
# Value: int
                                 8
tab-width:
text-column:
# Maximum word-length for COBOL words / Programmer defined words
# Be aware that GC checks the word length against COB_MAX_WORDLEN
# first (currently 63)
word-length:
                                 63
```

```
# Maximum literal size in general
literal-length:
                              8191
# Maximum numeric literal size (absolute maximum: 38)
numeric-literal-length:
                              38
# Maximum number of characters allowed in the character-string (max. 255)
pic-length:
                              255
# Default assign type
# Value: 'dynamic', 'external'
assign-clause:
                              dynamic
# If yes, file names are resolved at run time using
# environment variables.
# For example, given ASSIGN TO "DATAFILE", the file name will be
# 1. the value of environment variable 'DD_DATAFILE' or
# 2. the value of environment variable 'dd_DATAFILE' or
# 3. the value of environment variable 'DATAFILE' or
# 4. the literal "DATAFILE"
# If no, the value of the assign clause is the file name.
filename-mapping:
                              yes
# Alternate formatting of numeric fields
pretty-display:
# Allow complex OCCURS DEPENDING ON
complex-odo:
                              no
# Allow REDEFINES to other than last equal level number
indirect-redefines:
\# Binary byte size - defines the allocated bytes according to PIC
# Value: signed unsigned bytes
               -----
              1 - 4 same
5 - 9 same
# '2-4-8'
                                    4
#
             10 - 18 same
                                   8
#
# '1-2-4-8'
              1 - 2
                       same
                                    1
               3 - 4 same
               5 - 9 same
#
                       same
                                   8
#
               10 - 18
               1 - 2
# '1--8'
                        1 - 2
                                   1
                         3 - 4
               3 - 4
#
                                    2
               5 - 6 5 - 7
#
                                   3
               7 - 9
                        8 - 9
#
                                   4
#
               10 - 11
                        10 - 12
```

```
12 - 14 13 - 14
                                      6
               15 - 16 15 - 16
#
                                     7
               17 - 18 17 - 18 8
#
binary-size:
                               1-2-4-8
# Numeric truncation according to ANSI
binary-truncate:
                               ves
# Binary byte order
# Value: 'native', 'big-endian'
binary-byteorder:
                               big-endian
# Allow larger REDEFINES items
larger-redefines-ok:
                               no
# Allow certain syntax variations (eg. REDEFINES position)
relax-syntax-checks:
                               no
# Allow zero length reference-modification
# (only checked with active EC-BOUND-REF-MOD)
ref-mod-zero-length:
                               yes
# Perform type OSVS - If yes, the exit point of any currently
# executing perform is recognized if reached.
perform-osvs:
# Compute intermediate decimal results like IBM OSVS
arithmetic-osvs:
# MOVE like IBM (mvc); left to right, byte by byte
move-ibm:
                               nο
# SELECT RELATIVE KEY and ASSIGN fields must be in WORKING-STORAGE
select-working:
                       no
# LOCAL-STORAGE SECTION implies RECURSIVE attribute
local-implies-recursive:
                                       no
# If yes, LINKAGE SECTION items remain allocated
# between invocations.
sticky-linkage:
                               no
# If yes, allow non-matching level numbers
relax-level-hierarchy:
                               no
# If yes, evaluate constant expressions at compile time
constant-folding:
                               yes
# Allow Hex 'F' for NUMERIC test of signed PACKED DECIMAL field
hostsign:
                               no
```

```
# If yes, set WITH UPDATE clause as default for ACCEPT dest-item,
# except if WITH NO UPDATE clause is used
accept-update:
# If yes, set WITH AUTO clause as default for ACCEPT dest-item,
# except if WITH TAB clause is used
accept-auto:
# If yes, DISPLAYs and ACCEPTs are, by default, done on the CRT (i.e., using
# curses).
console-is-crt:
                                no
# If yes, allow redefinition of the current program's name. This prevents its
# use in a prototype-format CALL/CANCEL statement.
program-name-redefinition:
                                yes
# If yes, NO ECHO/NO-ECHO/OFF is the same as SECURE (hiding input with
# asterisks, not spaces).
no-echo-means-secure:
                                no
# If yes, the first item in a field screen ACCEPT/DISPLAY (e.g. DISPLAY x UPON
# CRT) is located after the previous ACCEPT/DISPLAY (as though LINE 0 COL 0 had
# been specified).
line-col-zero-default:
                                yes
# If yes, DISPLAY SPACES acts as ERASE EOS, DISPLAY X"01" acts as ERASE EOL,
# DISPLAY X"02" acts as BLANK SCREEEN and DISPLAY X"07" acts as BELL. Note
# DISPLAY LOW-VALUE is excluded from this; it will always just position the
# cursor.
display-special-fig-consts:
# If yes, COMP-1 is a signed 16-bit integer and any PICTURE clause is ignored.
binary-comp-1:
# If yes, POINTER is handled as BINARY-DOUBLE UNSIGNED instead of its own class
numeric-pointer:
# auto-adjust to zero like MicroFocus does
move-non-numeric-lit-to-numeric-is-zero: no
# If yes, implicitly define a variable for an ASSIGN DYNAMIC which does not
# match an existing data item.
implicit-assign-dynamic-var:
# What rules to apply to SCREEN SECTION items clauses
screen-section-rules:
# Whether DECIMAL-POINT IS COMMA has effect in XML/JSON GENERATE
dpc-in-data:
                                rm1
```

```
# Dialect features
# Value: 'ok', 'warning', 'archaic', 'obsolete', 'skip', 'ignore', 'error',
         'unconformable'
alter-statement:
                                         obsolete
                                         obsolete
comment-paragraphs:
call-overflow:
                                         archaic
data-records-clause:
                                         obsolete
debugging-mode:
                                         ok
use-for-debugging:
                                         ok
listing-statements:
                                         skip
                                                  # may be a user-defined word
title-statement:
                                                  # may be a user-defined word
                                         skip
entry-statement:
                                         ok
                                         obsolete
goto-statement-without-name:
label-records-clause:
                                         obsolete
memory-size-clause:
                                         obsolete
move-noninteger-to-alphanumeric:
                                         error
move-figurative-constant-to-numeric:
                                         archaic
move-figurative-space-to-numeric:
                                         error
move-figurative-quote-to-numeric:
                                         obsolete
multiple-file-tape-clause:
                                         obsolete
next-sentence-phrase:
                                         archaic
odo-without-to:
                                         warning
padding-character-clause:
                                         obsolete
section-segments:
                                         ignore
stop-literal-statement:
                                         obsolete
stop-identifier-statement:
                                         obsolete
same-as-clause:
                                         ok
type-to-clause:
                                         οk
usage-type:
                                                  ok
synchronized-clause:
                                         ok
special-names-clause:
                                         ok
top-level-occurs-clause:
                                         ok
value-of-clause:
                                         obsolete
numeric-boolean:
                                         ok
hexadecimal-boolean:
                                         ok
national-literals:
                                         ok
hexadecimal-national-literals:
                                         ok
national-character-literals:
                                         warning
# TO-DO: Add separate config option for H"..." to be unsupported, numeric, non-numeric (acu)
                                         unconformable
acu-literals:
hp-octal-literals:
                                         unconformable
word-continuation:
                                         warning
not-exception-before-exception:
                                         ok
accept-display-extensions:
                                         ok
renames-uncommon-levels:
                                         ok
symbolic-constant:
                                         ok
constant-78:
                                         ok
constant-01:
                                         ok
perform-varying-without-by:
                                         ok
reference-out-of-declaratives:
                                         warning
```

program-prototypes: ok call-convention-mnemonic: ok call-convention-linkage: ok numeric-value-for-edited-item: ok incorrect-conf-sec-order: ok define-constant-directive: archaic free-redefines-position: warning records-mismatch-record-clause warning record-delimiter: ok sequential-delimiters: οk record-delim-with-fixed-recs: ok missing-statement: warning zero-length-literals: ok xml-generate-extra-phrases: ok continue-after: ok goto-entry: warning assign-variable: ok assign-using-variable: ok assign-ext-dyn: ok

use complete word list; synonyms and exceptions are specified below reserved-words: default

ok

ignore

not-reserved:

assign-disk-from:

vsam-status:

Value: Word to be taken out of the reserved words list

not-reserved: TERMINAL

reserved:

Entries of the form word-1=word-2 define word-1 as an alias for default

reserved word word-2. No spaces are allowed around the equal sign.

reserved: AUTO-SKIP=AUTO
reserved: AUTOTERMINATE=AUTO
reserved: BACKGROUND-COLOUR=BACKGROUND-COLOR

reserved: BEEP=BELL

reserved:

BINARY-INT=BINARY-LONG
BINARY-LONG-LONG=BINARY-DOUBLE
CELLS=CELL reserved:

reserved: CELLS=CELL reserved: COLOURS=COLORS

EMPTY-CHECK=REQUIRED reserved:

EQUALS=EQUAL reserved:

reserved: FOREGROUND-COLOUR=FOREGROUND-COLOR

HIGH-VALUES=HIGH-VALUE reserved: reserved: INITIALISE=INITIALIZE INITIALISED=INITIALIZED reserved:

reserved: LENGTH-CHECK=FULL reserved: LOW-VALUES=LOW-VALUE reserved: ORGANISATION=ORGANIZATION

reserved: PIXELS=PIXEL

SYNCHRONISED=SYNCHRONIZED reserved:

TIMEOUT=TIME-OUT reserved:

reserved: VALUES=VALUE
reserved: ZEROES=ZERO
reserved: ZEROS=ZERO

10.2. Running Programs

Once GnuCOBOL programs have been compiled into either directly-executable programs (created via the -x switch) or dynamically-loadable libraries (created via the -m switch), those programs may be executed from any shell environment. The exact manner in which the two are executed will differ, as described in the upcoming sections.

10.2.1. Direct Execution

GnuCOBOL programs compiled with the -x switch will be generated as directly-executable programs. For example, a native Windows or Windows/MinGW build of GnuCOBOL will generate an .exe file when the -x switch switch is specified to the compiler.

On Unix, OSX, or Windows/Cygwin builds, the -x switch switch will generate an executable binary file, usually with no particular extension unless one is explicitly requested of the compiler via the -o switch.

On a UNIX system this means the programs may be executed from a command shell such as bash, csh, ksh and so forth. When a GnuCOBOL program runs on a Windows system, it runs within a console window (i.e. cmd.exe). OSX versions of GnuCOBOL programs run within a terminal.app window.

Interactions between the program and the user will take place using the standard input, standard output and standard error streams. Any screen section I/O performed by the program will take place within the terminal window.

Direct program execution syntax is [path]program [arguments].

For example:

/usr/local/printaccount ACCT=6625378

or

C:\\Users\\Me\\Documents\\Programs\\printaccount.exe ACCT=6625378

10.2.2. Executing Dynamically-Loadable Libraries

As discussed previously, dynamically-loadable libraries are created via the compiler's -m switch. Once so created, the program(s) in these libraries are executed from the command line (via the GnuCOBOL cobcrun utility), or as dynamically-loadable subprograms.

10.2.2.1. cobcrun - Command-line Execution

It is possible to generate executable modules for all GnuCOBOL programs, not just subprograms, by choosing to use the —m switch option to specify the loader output format, even for main programs.

Some may prefer to compile their GnuCOBOL main programs into these dynamically-loadable modules in the interests of using the same general compilation command for all programs without having to think "Is it a main program or a subprogram?".

Main programs compiled in this manner should be executed as follows:

[path]cobcrun program [arguments]

Do not specify the .so or .dll extension on the program name. The *program* value must exactly match the primary entry-point name of the main program (including upper- and lower-case letters), unless you are planning on using *Call Folding* (see [Dynamically Loaded Subprograms], page 583).

The general usage and syntax of cobcrun is as follows as issued by running cobcrun -h (or -help):

GnuCOBOL module loader

```
Usage: cobcrun [options] PROGRAM [parameter ...]
  or: cobcrun options
Options:
  -h, -help
                                 display this help and exit
  -V, -version
                                 display cobcrun and runtime version and exit
  -i, -info
                                 display runtime information (build/environment)
  -v, -verbose
                                 display extended output with --info
  -c <file>, -config=<file>
                                 set runtime configuration from <file>
  -r, -runtime-config
                                 display current runtime configuration
                                 (value and origin for all settings)
  -M <module>, -module=<module>
                                 set entry point module name and/or load path
                                 where -M module prepends any directory to the
                                 dynamic link loader library search path
                                 and any basename to the module preload list
                                 (COB_LIBRARY_PATH and/or COB_PRELOAD)
```

Here are two examples of using cobcrun. First, on a Unix, OSX or Windows/Cygwin system:

```
cd /usr/local
cobcrun printaccount acct=6625378
```

Or, on a Native Windows or Windows/MinGW system:

```
cd C:\Users\Me\Documents\Programs
cobcrun printaccount.exe acct=6625378
```

Note how the cobcrun command does not allow a path to be specified with the program name — the directory in which the programs dynamically loadable module exists must either be the current directory or must be defined in the current PATH.

10.2.2.2. Dynamically Loaded Subprograms

Dynamically-loaded subprograms are executed (from a COBOL syntax point of view) just like any other subprograms. What makes them unique, however, is that they are loaded into memory only when they are actually used the first time during the execution of a program.

When a dynamically-loadable module needs to be loaded (because it is not already in memory from a previous subprogram execution), the dynamically-loadable library will be sought by libcob in each directory named in the library specified by the COB\_LIBRARY\_PATH run-time environment variable will be searched and if not found then PATH run-time environment variable (see [Run Time Environment Variables], page 584) will be searched. Finally, if it *still* cannot be located, execution will be terminated with an error message (*libcob: Cannot find module 'xxxxxxxxx'*). For speed performance purposes all such should therefore be stored within the directories pointed to by the environment variable COB\_LIBRARY\_PATH run-time environment variable.

The process of locating dynamically-loadable modules is case-sensitive on UNIX systems; CALL "dynsub" and CALL "DYNSUB" will both fail to locate the DynSub.so library on a UNIX system.

Windows implementations of GnuCOBOL may, or may not, be similarly case sensitive with regard to library names, depending upon the Windows version and GnuCOBOL build options — it is safest to simply treat library names as case-sensitive in all environments.

It is possible, however, to automatically cause all library names to 'fold' to upper-case by specifying the <code>-ffold-call</code> switch with the "upper" option (i.e. <code>--fold-call=upper</code>) to the GnuCOBOL compiler. Similarly, library names could be folded to lower-case by using the "lower" option (i.e. <code>--fold-call=lower</code>. If libraries are maintained entirely using upper- or lower-case file names, either of these options will allow libraries to be found regardless of how the programmer entered their names on CALL statements.

See [Sub-Programming], page 603, for a complete discussion of sub-programming.

10.2.3. Run Time Environment Variables

The following is a list of the various environment variables that can play a role in the execution of GnuCOBOL programs.

COB\_DISPLAY\_WARNINGS

If set to a value of 'Y', any run-time warnings (such as noting the implicit closing of open files when a GOBACK statement (see [GOBACK], page 287) or STOP statement (see [STOP], page 345) with the RUN option is executed) will be displayed. Any other value for this environment variable (including not setting the variable at all) will suppress such messages.

COB\_LIBRARY\_PATH

At runtime, GnuCOBOL will attempt to locate and load any application dynamically loadable libraries used this variable that points to the directories specified, if it wasn't found there, using the PATH environment variable.

COB\_LOAD\_CASE

If set to either UPPER or LOWER, this environment variable will internally convert referenced entry-point names to either upper- or lower-case before initiating searches for dynamically-loadable modules. The UPPER and LOWER values of the environment variable are actually case-insensitive.

COB\_PHYSICAL\_CANCEL

If set to 'Y', 'y' or '1', a CANCEL statement (see [CANCEL], page 257) will physically unload a subprogram dynamically-loadable module. If set to anything else, a CANCEL statement (see [CANCEL], page 257) logically unloads a module so that subsequent use will re-initialize the module as if it had actually been reloaded, but the overhead of actually reloading the module will be avoided.

COB\_PRE\_LOAD

If set to any non-null value, this variable will cause all dynamically-loadable libraries to be loaded when the program begins execution (rather than searching for and loading the module upon first use).

COB\_SET\_DEBUG

If a USE FOR DEBUGGING (see [DECLARATIVES], page 218) section exists, the code within it will be disabled unless this environment variable is set to a value of 'Y', 'y' or '1'.

COB\_SET\_TRACE

If the <code>-ftrace</code> switch (trace procedures) or <code>-ftraceall</code> switch (trace procedures and statements) was used when the program was compiled, setting this environment variable to a value of 'Y' will activate the trace at the point the program begins execution. Setting this environment variable to any other value (or never setting it to ANY value) will disable tracing. Tracing, if configured by one of the two switches described above, can also be controlled via the <code>READY TRACE</code> statement (see

[READY TRACE], page 320) and RESET TRACE statement (see [RESET TRACE], page 322). If COB\_SET\_TRACE is set to Y, then tracing will always occur regardless of the presence of READY TRACE or RESET TRACE so in effect they will have no action on program execution.

COB\_SCREEN\_ESC

If set to any non-blank value, this variable allows a ACCEPT data-item statement (see [ACCEPT data-item], page 234) to detect the Esc key.

COB\_SCREEN\_EXCEPTIONS

Setting this variable to any non-blank value will allow the ACCEPT data-item statement (see [ACCEPT data-item], page 234) to detect the pressing of the Esc, PgUp and PgDn keys.

COB\_SORT\_MEMORY

The value of this variable (an integer) will be used to define how much memory will be allocated for use in sorting. If the value is 1048576 or greater, that value will be used "as is" as the amount of memory (in bytes) to allocate. If the value is less than 1048576, the value will specify how many MB of memory will be allocated. The default sort memory amount is 128 MB.

COB\_SWITCH\_n

(n=0 to 15); These environment variables correspond to SWITCH-0 through SWITCH-15, defined in the SPECIAL-NAMES (see [SPECIAL-NAMES], page 84) paragraph. Setting them to ON will activate them; any other value turns them off.

COB\_SYNC If set to a value of upper- or lower-case 'p', this variable will force a file commit every time a file is written to (ensuring that data is immediately written to the file rather than retained in memory until a future commit occurs). This will slow-down update access to files, but will provide for better integrity in the event of a program failure.

COB\_TRACE\_FILE

If set to any non-null value, this environment variable specifies the file to which all -ftrace switch and -ftraceall switch output will be written. If this is NOT set to a value, all -ftrace switch and -ftraceall switch output will be written to STDERR, where it may be piped via a "2> filename" on the command that executes the program.

DB\_HOME If your GnuCOBOL build uses the Berkeley Database (BDB) package, use this environment variable to specify the folder in which the lock management files to be associated with all non-SORT files opened by the program will be stored. ORGANIZATION INDEXED (see [ORGANIZATION INDEXED], page 105) files will also have their data file allocated in the folder pointed to by this environment variable, if it exists. Having this variable defined will activate record locking features on the READ statement (see [READ], page 316), REWRITE statement (see [REWRITE], page 324) and WRITE statement (see [WRITE], page 360). Even with DB\_HOME, locking will not work with ORGANIZATION SEQUENTIAL (see [ORGANIZATION SEQUENTIAL], page 100), ORGANIZATION LINE SEQUENTIAL (see [ORGANIZATION LINE SEQUENTIAL], page 101) or ORGANIZATION RELATIVE files with GnuCOBOL builds created for Windows/MinGW. ORGANIZATION INDEXED locks will work with Windows/MinGW + BDB and all locks will work for all file organizations with UNIX GnuCOBOL builds.

PATH The GnuCOBOL "bin" directory should be defined in the PATH.

TMPDIR

TMP TEMP

One of these environment variables must be set to a directory/folder appropriate to create temporary files in. They will be checked in the order shown. This will be used by the SORT statement (see [SORT], page 339) and MERGE statement (see [MERGE], page 302) to create temporary work files. You may also use this folder for any temporary files your application may require.

Also used during execution of programs is runtime.cfg also found in /usr/local/share/gnucobol/config for \*nix and this file can also be changed to match your environment if needed. When viewing, note the Default settings.

10.2.3.1. General instructions

The initial runtime.cfg file is found in the $COB_CONFIG_DIR/config$ (COB_CONFIG_DIR defaults to installdir/gnucobol). The environment variable $COB_RUNTIME_CONFIG$ may define a different runtime

The environment variable COB\_RUNTIME\_CONFIG may define a different runtime configuration file to read.

If settings are included in the runtime environment file multiple times then the last setting value is used, no warning occurs.

Settings via environment variables always take precedence over settings that are given in runtime configuration files. And the environment is checked after completing processing of the runtime configuration file(s)

All values set to string variables or environment variables are checked for \${envvar} and replacement is done at the time of the setting.

Any environment variable may be set with the directive setenv . Example: setenv COB\_LIBRARY\_PATH \${LD\_LIBRARY\_PATH}

Any environment variable may be unset with the directive unsetenv (one var per line).

Example: unsetenv COB\_LIBRARY\_PATH

Runtime configuration files can include other files with the directive include.

Example: include my-runtime-configuration-file

To include another configuration file only if it is present use the directive includeif.

You can also use \${envvar} inside this.

Example: includeif \${HOME}/mygc.cfg

If you want to reset a parameter to its default value use: reset parametername

Most runtime variables have boolean values, some are switches, some have string values, integer values and some are size values.

The boolean values will be evaluated as following:

to true: 1, Y, ON, YES, TRUE (no matter of case)

to false: 0, N, OFF

A 'size' value is an integer optionally followed by K, M, or G for kilo, mega or giga.

For convenience a parameter in the runtime.cfg file may be defined by using either the environment variable name or the parameter name.

In most cases the environment variable name is the parameter name (in upper case) with the prefix $\mbox{COB}_{\_}$.

Note: If you want to \*slightly\* speed up a program's startup time, remove all of the comments from the actual real configuration file that is processed

10.2.3.2. General Environment

Environment name: COB\_DISABLE\_WARNINGS
Parameter name: disable\_warnings

Purpose: turn off runtime warning messages

Type: boolean Default: false

Example: DISABLE\_WARNINGS TRUE

Environment name: COB\_ENV\_MANGLE Parameter name: env\_mangle

Purpose: names checked in the environment would get non alphanumeric

change to '\_'

Type: boolean Default: false

Example: ENV\_MANGLE TRUE

Environment name: COB\_SET\_DEBUG
Parameter name: debugging\_mode

Purpose: to enable USE ON DEBUGGING procedures that were active

during compile-time because of WITH DEBUGGING MODE,

otherwise the code generated will be skipped

Type: boolean Default: false

Example: COB\_SET\_DEBUG 1

Environment name: COB\_SET\_TRACE
Parameter name: set\_trace

Purpose: to enable COBOL trace feature

Type: boolean Default: false

Example: SET\_TRACE TRUE

Environment name: COB\_TRACE\_FILE Parameter name: trace\_file

Purpose: to define where COBOL trace output should go

Type: string
Default: stderr

Example: TRACE\_FILE \${HOME}/mytrace.log

Environment name: COB\_TRACE\_FORMAT Parameter name: trace\_format

Purpose: to define format of COBOL trace output

Type: string

Default: "%P %S Line: %L"

%P is replaced by Program-Id/Function-Id minimal length 29

with prefix

%I is replaced by Program-Id/Function-Id variable length,

without prefix

%L is replaced by Line number, right justified, length 6

%S is replaced by statement type and name

%F is replaced by source file name

Example: TRACE\_FORMAT "Line: %L %S" Note: format of GC2.2 and older:

"PROGRAM-ID: %I Line: %L %S"

For v4.0+

Environment name: COB\_TRACE\_IO Parameter name: trace\_io

Purpose: define if I/O details should be added to trace

Type: boolean Default: false

Example: TRACE\_IO true

Environment name: COB\_DUMP\_FILE Parameter name: dump\_file

Purpose: to define where COBOL dump output should go
Note: The -fdump=all compile option prepares for dump
Type: string : \$\$ is replaced by process id

Default: stderr

Example: DUMP\_FILE \${HOME}/mytrace.log

Environment name: COB\_DUMP\_WIDTH Parameter name: dump\_width

Purpose: to define COBOL dump line length

Type: integer Default: 100

Example: dump\_width 120

For v4.0+

Environment name: COB\_STATS\_RECORD Parameter name: stats\_record

Purpose: define if I/O statistics should be written

Type: boolean Default: false

Example: STATS\_RECORD true

For v4.0+

Environment name: COB\_STATS\_FILE

Parameter name: stats\_file

Purpose: to define where COBOL I/O statistics should be written

The file is appended to

Type: string Default: stderr

Example: STATS\_FILE \${HOME}/mystats.txt

Environment name: COB\_CURRENT\_DATE
Parameter name: current\_date

Purpose: specify an alternate Date/Time to be returned to ACCEPT clauses this is used for testing purposes or to tweak

a missing offset partial setting is allowed

Type: numeric string in format YYYYDDMMHH24MISS or date string

Default: the operating system date is used
Example: COB\_CURRENT\_DATE "2016/03/16 16:40:52"
current\_date YYYYMMDDHHMMSS+01:00

10.2.3.3. Call Environment

Environment name: COB\_LIBRARY\_PATH
Parameter name: library\_path

Purpose: paths for dynamically-loadable modules

Type: string

Note: the default paths .:/installpath/extras are always

added to the given paths

Example: LIBRARY\_PATH /opt/myapp/test:/opt/myapp/production

Environment name: COB\_PRE\_LOAD Parameter name: pre\_load

Purpose: modules that are loaded during startup, can be used

to CALL COBOL programs or C functions that are part

of a module library

Type: string

Note: the modules listed should NOT include extensions, the

runtime will use the right ones on the various platforms,

COB\_LIBRARY\_PATH is used to locate the modules

Example: PRE\_LOAD COBOL\_function\_library:external\_c\_library

Environment name: COB\_LOAD\_CASE
Parameter name: load case

Purpose: resolve ALL called program names to UPPER or LOWER case

Type: Only use UPPER or LOWER

Default: if not set program names in CALL are case sensitive

Example: LOAD\_CASE UPPER

Environment name: COB\_PHYSICAL\_CANCEL Parameter name: physical\_cancel

Purpose: physically unload a dynamically-loadable module on CANCEL,

this frees some RAM and allows the change of modules during

run-time but needs more time to resolve CALLs (both to

active and not-active programs)

Alias: default\_cancel\_mode, LOGICAL\_CANCELS (0 = yes)

Type: boolean (evaluated for true only)

Default: false

Example: PHYSICAL\_CANCEL TRUE

10.2.3.4. File I/O

Environment name: COB\_VARSEQ\_FORMAT Parameter name: varseq\_format

Purpose: declare format used for variable length sequential files

- different types and lengths precede each record

- 'length' is the data length, does not include the prefix

Type: 0 means 2 byte record length (big-endian) + 2 NULs

1 means 4 byte record length (big-endian)

2 means 4 byte record length (local machine int)

3 means 2 byte record length (big-endian)

Default: 0

Example: VARSEQ\_FORMAT 1

For v4.0+

Environment name: COB\_VARREL\_FORMAT Parameter name: varrel\_format

- - - - -

Purpose: declare format to be used for variable length relative files Type: gc means 'size\_t' record length (local machine) precedes

maxiumum length data record

mf means file is in Micro Focus format

b32 means Big-Endian 32-bit 'int' record length precedes data

b64 means Big-Endian 64-bit 'int' record length precedes data

132 means Little-Endian 32-bit 'int' record length precedes data

164 means Little-Endian 64-bit 'int' record length precedes data

Default: gc

NOTE: 'gc' results in files which cannot be used if copied between

machines of different hardware archeticture

Example: VARREL\_FORMAT mf

For v4.0+

Environment name: COB\_FIXREL\_FORMAT

Parameter name: fixrel\_format

Purpose: declare format to be used for fixed length relative

files (different types and lengths preceding each record)

Type: b32 means 4 byte record length (big-endian)

132 means 4 byte record length (little-endian) b64 means 8 byte record length (big-endian) 164 means 8 byte record length (little-endian)

mf means Micro Focus default

gc means GnuCOBOL default (local 'size\_t')

Default: gc fixed size with no record length prefix

Example: FIXREL\_FORMAT B32

For v4.0+

Environment name: COB\_VARFIX\_FORMAT
Parameter name: varfix\_format

Purpose: declare format to be used for fixed length relative files Type: gc means 'size\_t' record length (local machine) precedes

fixed length data record

mf means file is in Micro Focus format

b32 means Big-Endian 32-bit 'int' record length precedes data
b64 means Big-Endian 64-bit 'int' record length precedes data
132 means Little-Endian 32-bit 'int' record length precedes data
164 means Little-Endian 64-bit 'int' record length precedes data

Default: gc

NOTE: 'gc' results in files which cannot be used if copied between

machines of different hardware archeticture

Example: VARFIX\_FORMAT mf

Environment name: COB\_FILE\_PATH
Parameter name: file\_path

Purpose: define default location where data files are stored

Type: file path directory
Default: . (current directory)
Example: FILE\_PATH \${HOME}/mydata

Environment name: COB\_LS\_FIXED Parameter name: ls\_fixed

Purpose: Defines if LINE SEQUENTIAL files should be fixed length

(or variable, by removing trailing spaces)

Alias: STRIP\_TRAILING\_SPACES (0 = yes)

Type: boolean Default: false

Example: LS\_FIXED TRUE

Environment name: COB\_LS\_NULLS
Parameter name: ls\_nulls

Purpose: Defines for LINE SEQUENTIAL files what to do with data

which is not DISPLAY type. This could happen if a LINE SEQUENTIAL record has BINARY/COMP data fields in it. For v4.0+ (may change before its release candidate)

This option is only for GnuCOBOL format files

Type: boolean Default: false

Note: The TRUE setting will insert a null character x"00" before

those values to escape them, and redo on read-in.

Example: LS\_NULL = TRUE

For v4.0+

Environment name: COB\_LS\_SPLIT Parameter name: ls\_split

Purpose: Defines for LINE SEQUENTIAL files what to do when a record

is longer than the program handles. If 'ls\_split=true' then

the data is returned as multiple records

Type: boolean Default: false

The record is truncated and the file skips to the next LF

Example: LS\_SPLIT = TRUE

For v4.0+

Environment name: COB\_LS\_VALIDATE
Parameter name: ls\_validate

Purpose: Defines for LINE SEQUENTIAL files that the data should be

validated. If any record has non-DISPLAY characters then

an error status of 34 is returned

For v4.0+ (may change before its release candidate)

This option is only for GnuCOBOL format files

Type: boolean Default: true

Note: The TRUE setting does data validation

The FALSE setting lets non-DISPLAY characters be written

If LS\_NULLS is set, then LS\_VALIDATE is not checked

Example: LS\_VALIDATE = FALSE

For v4.0+ (may be replaced before its release candidate)

Environment name: COB\_MF\_FILES Parameter name: mf\_files

Purpose: Declares that all files in the program should be in

Micro Focus compatible format.

Type: boolean (evaluated for true only)

Default: false

Example: mf\_files True

For v4.0+ (may be replaced before its release candidate)

Environment name: COB\_MF\_LS\_NULLS Parameter name: mf\_ls\_nulls

Purpose: Defines for Micro Focus compatible LINE SEQUENTIAL files

what to do with data which is not DISPLAY type. This could happen if a LINE SEQUENTIAL record has

BINARY/COMP data fields in it.

Type: boolean Default: true

Note: The TRUE setting will handle files that contain COMP data

in a similar manner to the method used by Micro Focus COBOL

Example: MF\_LS\_NULLS = TRUE

For v4.0+ (may be replaced before its release candidate)

Environment name: COB\_MF\_LS\_INSTAB
Parameter name: mf\_ls\_instab

Purpose: Defines for LINE SEQUENTIAL files that multiple spaces

should be replaced by a TAB character, assuming a 'tab set' value of 8. Each TAB means to skip to the next column that

is a multiple of 8

Similar to Micro Focus INSERTTAB=ON option

Type: boolean Default: false

Example: MF\_LS\_INSTAB = TRUE

For v4.0+ (may be replaced before its release candidate)

Environment name: COB\_MF\_LS\_SPLIT
Parameter name: mf\_ls\_split

Purpose: Defines for Micro Focus compatible LINE SEQUENTIAL files what

to do when a record is longer than the program handles.

If 'mf\_ls\_split=true' then

the data is returned as multiple records

Type: boolean
Default: true

Example: MF\_LS\_SPLIT = FALSE

For v4.0+ (may be replaced before its release candidate)

Environment name: COB\_MF\_LS\_VALIDATE Parameter name: mf\_ls\_validate

Purpose: Defines for Micro Focus compatible LINE SEQUENTIAL files

that the data should be validated.

If any record has non-DISPLAY characters then

an error status of 34 is returned

Type: boolean Default: false

Note: The TRUE setting does data validation

The FALSE setting lets non-DISPLAY characters be written If MF\_LS\_NULLS is set, then MF\_LS\_VALIDATE is not checked

Example: MF\_LS\_VALIDATE = FALSE

For v4.0+

Environment name: COB\_SHARE\_MODE Parameter name: share\_mode

Purpose: Defines what file sharing option should be used

Type: -- choice of values ---

none - nothing overrides application code
read - files opened as SHARE READ ONLY
all - files opened as SHARE ALL OTHERS
no - files opened as SHARE NO OTHERS

Default: none

Example: share\_mode = ALL

For v4.0+

Environment name: COB\_RETRY\_MODE Parameter name: retry\_mode

Purpose: Defines what I/O retry sharing option should be used

Type: --- choice of values ---

none - nothing overrides application code

never - I/O is never retried

forever - I/O will be retried until success

Default: none

Example: retry\_mode = never

For v4.0+

Environment name: COB\_RETRY\_TIMES Parameter name: retry\_times

Purpose: Defines how many times I/O should be retried

Type: integer

Default: 0

Example: retry\_times = 10

For v4.0+

Environment name: COB\_RETRY\_SECONDS Parameter name: retry\_seconds

Purpose: Defines how many seconds I/O should be retried

Type: integer

Default: 0

Example: retry\_seconds = 6

For v4.0+

Environment name: COB\_KEYCHECK Parameter name: keycheck

Purpose: Must INDEXED file keys match COBOL SELECT exactly

Type: boolean Default: true

Example: keycheck = off

Environment name: COB\_SYNC Parameter name: sync

Purpose: Should the file be synced to disk after each write/update

Type: boolean
Default: false
Example: SYNC: TRUE

Environment name: COB\_SORT\_MEMORY
Parameter name: sort\_memory

Purpose: Defines how much RAM to assign for sorting data if this size is exceeded the SORT will be done

on disk instead of memory

Type: size but must be more than 1M

Default: 128M

Example: SORT\_MEMORY 64M

Environment name: COB\_SORT\_CHUNK Parameter name: sort\_chunk

Purpose: Defines how much RAM to assign for sorting data in chunks $% \left(1\right) =\left(1\right) \left(1\right) +\left(1\right) \left(1\right) \left(1\right) +\left(1\right) \left(1\right$

Type: size but must be within 128K and 16M

Default: 256K

Example: SORT\_CHUNK 1M

10.2.3.5. Screen I/O

Environment name: COB\_BELL Parameter name: bell

Purpose: Defines how a request for the screen to beep is handled

Type: FLASH, SPEAKER, FALSE, BEEP

Default: BEEP

Example: BELL SPEAKER

Environment name: COB\_REDIRECT\_DISPLAY Parameter name: redirect\_display

Purpose: Defines if DISPLAY output should be sent to 'stderr'

Type: boolean Default: false

Example: redirect\_display Yes

Environment name: COB\_SCREEN\_ESC Parameter name: screen\_esc

Purpose: Enable handling of ESC key during ACCEPT

Type: boolean Default: false

Note: is only evaluated if COB\_SCREEN\_EXCEPTIONS is active

Example: screen\_esc Yes

Environment name: COB\_SCREEN\_EXCEPTIONS
Parameter name: screen\_exceptions

Purpose: enable exceptions for function keys during ACCEPT

Type: boolean Default: false

Example: screen\_exceptions Yes

Environment name: COB\_TIMEOUT\_SCALE Parameter name: timeout\_scale

Purpose: specify translation in milliseconds for ACCEPT clauses

BEFORE TIME value / AFTER TIMEOUT

Type: integer

O means 1000 (Micro Focus COBOL compatible), 1 means 100

(ACUCOBOL compatible), 2 means 10, 3 means 1

Default: 0

Example: timeout\_scale 3

Environment name: COB\_INSERT\_MODE Parameter name: insert\_mode

Purpose: specify default insert mode for ACCEPT; 0=off, 1=on

Type: boolean Default: false

Note: also sets the cursor type (if available)

Example: insert\_mode Y

Environment name: COB\_MOUSE\_FLAGS

Parameter name: mouse\_flags

Purpose: specify which mouse events will be sent as function key

to the application during ACCEPT and how they will be

handled

Type: int (by bits)

Default: 1

Note: O disables the mouse cursor, any other value enables it,

any value containing 1 will enable internal handling (click

to position, double-click to enter).

See copy/screenio.cpy for list of events and their values.

Alias: MOUSE\_FLAGS

Example: 11 (enable internal handling => 1, left press => 2,

double-click => 8; 1+2+8=11)

Environment name: COB\_MOUSE\_INTERVAL

Parameter name: mouse\_interval

Purpose: specifies the maximum time (in thousands of a second)

that can elapse between press and release events for them

to be recognized as a click.

Type: int (0 - 166)

Default: 100

Note: O disables the click resolution (instead press + release

are recognized), also disables positioning by mouse click

Environment name: COB\_DISPLAY\_PRINT\_PIPE

Parameter name: display\_print\_pipe

Purpose: Defines command line used for sending output of

DISPLAY UPON PRINTER to (via pipe)

This is very similar to Micro Focus COBPRINTER

Note: Each executed DISPLAY UPON PRINTER statement causes a

new invocation of command-line (= new process start).

Each invocation receives the data referenced in the DISPLAY statement and is followed by an

end-of-file condition.

COB\_DISPLAY\_PRINT\_FILE, if set, takes precedence

over COB\_DISPLAY\_PRINT\_PIPE.

Alias: COBPRINTER Type: string

Default: not set

Example: print 'cat >>/tmp/myprt.log'

Environment name: COB\_DISPLAY\_PRINT\_FILE

Parameter name: display\_print\_file

Purpose: Defines file to be appended to by DISPLAY UPON PRINTER

Note: Each DISPLAY UPON PRINTER opens, appends and closes the file.

Type: string : \$\$ is replaced by process id

Default: not set

Example: display\_printer '/tmp/myprt.log'

Environment name: COB\_DISPLAY\_PUNCH\_FILE

Parameter name: display\_punch\_file

Purpose: Defines file to be created on first

DISPLAY UPON SYSPUNCH/SYSPCH

Note: The file will be only be closed on runtime exit.

Type: string: \$\\$\$ is replaced by process id

Default: not set

Example: display\_punch './punch\_\$\$.out'

Environment name: COB\_LEGACY
Parameter name: legacy

Purpose: keep behaviour of former runtime versions, currently only

for setting screen attributes for non input fields

Type: boolean
Default: not set
Example: legacy true

Environment name: COB\_EXIT\_WAIT Parameter name: exit\_wait

Purpose: to wait on main program exit if an extended screenio

DISPLAY was issued without an ACCEPT following

Type: boolean Default: true

Example: COB\_EXIT\_WAIT off

Environment name: COB\_EXIT\_MSG Parameter name: exit\_msg

Purpose: string to display if COB\_EXIT\_WAIT is processed, set to '@w{}'

if no actual display but an ACCEPT should be done

Type: string

Default: 'end of program, please press a key to exit' (localized)

Example: COB\_EXIT\_MSG '@w{}'

10.2.3.6. Report I/O

Environment name: COB\_COL\_JUST\_LRC Parameter name: col\_just\_lrc

Purpose: If true, then COLUMN defined as LEFT, RIGHT or CENTER will have the data justified within the field limits

If false, then the data is just copied into the column as is

Type: boolean Default: TRUE

Example: col\_just\_lrc True

10.2.3.7. File I/O Environment Variables and/or dictionary file

GnuCOBOL 4.+ only!

Before a file is opened a check is done for environment variables that may define various attributes of the file First a check is made for attributes for files of the same ORGANIZATION

IX\_OPTIONS for INDEXED, SQ\_OPTIONS for SEQUENTIAL, RL\_OPTIONS for RELATIVE LS\_OPTIONS for LINE SEQUENTIAL, LA\_OPTIONS for LINE ADVANCING SEQUENTIAL If none of these are present, it then checks for IO\_OPTIONS

Then an additional check is done for IO\_asgnmame where 'asgname' was the ASSIGN EXTERNAL name used in the program

The environment variable (or dictionary file) may contain any of the following keywords, separated by spaces and/or commas

You can specify just the keyword and it is assumed to mean set to true, or no-keyword (or no\_keyword or nokeyword) which means set to false,

| or keyword=true | or keyword=false. The valid keywords are: |
|-----------------------------|--|
| Keyword | Meaning |
| ======= | |
| type=xx | Set file organization where 'xx' is one of |
| | IX = INDEXED, SQ = SEQUENTIAL, RL = RELATIVE |
| | LS = LINE SEQUENTIAL, LA = LINE ADVANCING |
| mf | Set file to Micro Focus compatible format |
| gc | Set to original GnuCOBOL default format |
| recsz | The size for fixed size record file |
| maxsz | Maximum record size for variable length records |
| minsz | Minimum record size for variable length records |
| ls_nulls | Do NUL insertion before characters less than a SPACE, |
| | Default: false |
| ls_validate | Validate data for LINE Sequential Files, Default: true |
| crlf | Lines end with CR LF (Windows format for text files) |
| lf | Lines end with LF (Unix format for text files) |
| sync | Sync all writes to disk |
| B32 | Use 32-bit Big-Endian format 'int' as record length |
| L32 | Use 32-bit Little-Endian format 'int' as record length |
| B64 | Use 64-bit Big-Endian format 'int' or 'size_t' as record length |
| L64 | Use 64-bit Little-Endian format 'int' or 'size_t' as record length |
| trace | Enable I/O trace when program execution tracing is enabled |
| stats | Write I/O statistic information on file close |
| retry_times | Default number of times to retry I/O |
| retry_seconds | Number of seconds between I/O retry attempts |
| retry_forever | Retry I/O forever |
| retry_never | Never retry I/O operations |
| ignore_lock | Ignore record locks |
| advancing_lock | Advance to the next record if lock condition |
| share_all | Share file with ALL others |
| share_read | Share file for READ only |
| share_no | Share file with NO others |
| | |
| For INDEXE | D files |
| <pre>format=ixhandler</pre> | INDEXED file format: CISAM, DISAM, VBISAM, BDB, LMDB |
| format=auto | INDEXED file format is determined by inspecting the file |
| nkeys=n | number of indexes |

key1=(loc:len) loc (zero relative) of key, len of key

key2=(loc:len,loc:len ...)

```
define composite index
dupn=Y index allows dups

---- For INDEXED BDB files -----
big_endian Set internal 'int' byte order to BIG ENDIAN
little_endian Set internal 'int' byte order to LITTLE ENDIAN
```

10.2.4. Program Arguments

Regardless of the manner in which a main program is executed (i.e. directly or via cobcrun), any arguments specified to the program may be retrieved via any of the following:

- ACCEPT FROM COMMAND-LINE (see [ACCEPT FROM COMMAND-LINE], page 231)
- PROCEDURE DIVISION CHAINING (see [PROCEDURE DIVISION CHAINING], page 214)

10.3. Binary Truncation

By default, the GnuCOBOL compiler will truncate binary data items to the precision indicated by their PICTURE (see [PICTURE], page 176) clause, if they have one. This applies to COMP, BINARY and COMP-4 items Only.

The fact is, however, that binary truncation has a significant effect on the performance of GnuCOBOL programs. When binary truncation is in effect, arithmetic operations performed against all types of numeric data items (even USAGE DISPLAY) are slowed down.

Before continuing, it's worth making the point that we're *not* talking about astronomical performance degradations here. Today's computers are *fast*, and a user sitting at the keyboard, running a GnuCOBOL program is unlikely to notice. But, if you have a GnuCOBOL program that has to process large amounts of data, performing some significant "number crunching" against that data as it goes, the impact of truncation could become noticeable.

The following program compares the performance of performing arithmetic operations (in a totally non-scientific, non-rigorous way) against data items with a USAGE (see [USAGE], page 198) of DISPLAY, COMP and BINARY-LONG. It was actually my intent when I first wrote the program to merely demonstrate the relative performance differences between different types of numeric data storage, and it certainly met that objective.

```
IDENTIFICATION DIVISION.
PROGRAM-ID. DEMOMATH.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 Begin-Time.
    05 BT-HH
                                PIC 9(2).
    05 BT-MM
                                PIC 9(2).
    05 BT-SS
                                PIC 9(2).
    05 BT-HU
                                PIC 9(2).
01 Binary-Item
                        BINARY-LONG SIGNED VALUE O.
01 Comp-Item
                        COMP
                                PIC S9(9) VALUE 0.
01 Display-Item
                        DISPLAY PIC S9(9) VALUE 0.
01 End-Time.
    05 ET-HH
                                PIC 9(2).
    05 ET-MM
                                PIC 9(2).
    05 ET-SS
                                PIC 9(2).
                                PIC 9(2).
    05 ET-HU
```

```
78 Repeat-Count
                                VALUE 10000000.
01 Time-Diff
                                PIC ZZ9.99.
PROCEDURE DIVISION.
010-Test-Usage-DISPLAY.
    ACCEPT Begin-Time FROM TIME
    PERFORM Repeat-Count TIMES
        ADD 7 TO Display-Item
    END-PERFORM
    PERFORM 100-Determine-Time-Diff
    DISPLAY 'USAGE DISPLAY: ' Time-Diff ' SECONDS'
020-Test-Usage-COMP.
    ACCEPT Begin-Time FROM TIME
    PERFORM Repeat-Count TIMES
        ADD 7 TO Comp-Item
    END-PERFORM
    PERFORM 100-Determine-Time-Diff
    DISPLAY 'USAGE COMP: ' Time-Diff ' SECONDS'
040-Test-Usage-BINARY.
    ACCEPT Begin-Time FROM TIME
    PERFORM Repeat-Count TIMES
       ADD 7 TO Binary-Item
    END-PERFORM
    PERFORM 100-Determine-Time-Diff
   DISPLAY 'USAGE BINARY: ' Time-Diff ' SECONDS'
099-Done.
   STOP RUN
100-Determine-Time-Diff.
    ACCEPT End-Time FROM TIME
    COMPUTE Time-Diff =
      (ET-HH * 360000 + ET-MM * 6000 + ET-SS * 100 + ET-HU)
      - (BT-HH * 360000 + BT-MM * 6000 + BT-SS * 100 + BT-HU) )
      / 100
```

Each data item has 7 added to it ten million times.

The time (to one-one-hundredth of a second) will be retrieved before and after each test and the difference between the two is displayed. This is why the computations were done so many times — it was to make sure the timing was measurable with only a 1/100 second "stopwatch".

I also ran the tests multiple times, just to make sure I had consistent results (I did). Like I mentioned earlier, this is not a rigorous, scientific benchmark of numeric performance; it's just a quick-and-dirty comparison.

Here are the results:

```
Test 1:
```

USAGE DISPLAY: 1.72 SECONDS USAGE COMP: 0.62 SECONDS USAGE BINARY: 0.02 SECONDS Test 2:

USAGE DISPLAY: 1.69 SECONDS USAGE COMP: 0.61 SECONDS USAGE BINARY: 0.02 SECONDS

Test 3:

USAGE DISPLAY: 1.69 SECONDS USAGE COMP: 0.65 SECONDS USAGE BINARY: 0.02 SECONDS

The results I saw here were consistent with those that would have been obtained from most of the COBOL implementations I have ever worked with — USAGE COMP has a significant performance advantage over USAGE DISPLAY and USAGE BINARY-LONG (and presumably the other BINARY-xxx usages as well) perform identically, within the measurement tolerances of the test.

Imagine my surprise, however, when I discovered that the use of <code>-fnotrunc</code> switch also made a difference:

Test 4:

USAGE DISPLAY: 1.72 SECONDS
USAGE COMP: 0.07 SECONDS
USAGE BINARY: 0.02 SECONDS

Test 5:

USAGE DISPLAY: 1.72 SECONDS USAGE COMP: 0.07 SECONDS USAGE BINARY: 0.02 SECONDS

Test 6:

USAGE DISPLAY: 1.73 SECONDS
USAGE COMP: 0.06 SECONDS
USAGE BINARY: 0.02 SECONDS

As you can see, there was a huge drop in USAGE COMP timings by turning off truncation. As a result, I see absolutely no reason whatsoever why the -fnotrunc switch option shouldn't be used on all GnuCOBOL compilations.

If you want to squeeze every last bit of performance out of your GnuCOBOL programs, don't forget to investigate the <code>-O</code> switch, <code>-O2</code> switch and the <code>-Os</code> switch, all of which influence the optimization of compiled code. Actually run programs using various optimization switches (or not) and compare execution times against those of unoptimized compiled versions of your programs. Don't just compare the generated C code because sometimes the differences can't be seen at the C source-code level.

Test 7:

cobc -x demomath.cbl -02;demomath
USAGE DISPLAY: 1.68 SECONDS
USAGE COMP: 0.60 SECONDS
USAGE BINARY: 0.00 SECONDS

Test 8:

cobc -x demomath.cbl -fnotrunc -02;demomath

USAGE DISPLAY: 1.67 SECONDS

USAGE COMP: 0.01 SECONDS USAGE BINARY: 0.00 SECONDS

All tests above carried out under Linux with a AMD FX8350 under very low loading prior to the test. I would have also tried on a i7-7700 but that is under Windows 10 and I do not have a GC version on it - Vince.

End of Chapter 10 — Interfacing With The OS

11. Sub-Programming

11.1. Subprogram Types

Simply stated, a *Subprogram* is a program that is invoked by another program; the subprogram performs whatever its designed operations are and — when complete — typically returns control back to the program that invoked it. There are two different types of subprograms supported by GnuCOBOL, subroutines and user-defined functions. The distinction between these two subprogram types lies in the manner in which they are executed.

When program A invokes subprogram B as a Subroutine, it does so using a special statement dedicated to that function (the CALL statement (see [CALL], page 253), just as if B were one of the built-in system subroutines.

When program A invokes program B as a User-Defined Function, it does so in a manner identical to how B would have been invoked had it been one of the many built-in intrinsic functions.

In either instance, program A is referred to as the *Calling Program* while program B is known as the *Called Program*. GnuCOBOL programs may be a calling program, a called program or both.

A program written in the C programming language may serve as either the calling or called program too. A called program may act as a calling program to another called program. When a calling program does not serve as a called program to any program, that calling program is known as a *Main Program*.

Both subroutines and user-defined functions may return a value. The value they return must be an integer in the range -2147483648 to +2147483647. This value will be available in the RETURN-CODE special register (see [Special Registers], page 227) and also as the value of the data item specified on the RETURNING (see [CALL], page 253) clause of a subroutine's CALL.

11.2. Independent vs Contained vs Nested Subprograms

Subprograms (either subroutines or user-defined functions) can be implemented in three different ways.

Independent Subprograms

These are subprograms that are coded as the only COBOL program in their Compilation Unit (see [Compilation Unit], page 567).

$Contained\ Subprograms$

These are subprograms which occur in the same Compilation Unit as a main program and/or other subprograms. Each contained subprogram is separated from the next via an END PROGRAM marker line. As an example. . .

```
IDENTIFICATION DIVISION.
PROGRAM-ID. SUB1.
...
END PROGRAM SUB1.
IDENTIFICATION DIVISION.
PROGRAM-ID. SUB2.
...
END PROGRAM SUB2.
```

Program source code may be concatenated as shown here, provided an END PROGRAM marker naming the PROGRAM-ID of the just-completed program is used to separate one program from another.

There's no reason that user-defined functions cannot be included too — they'll just have FUNCTION-IDs and will be ended by END FUNCTION markers.

The last program in any GnuCOBOL source file need not have an END marker.

When multiple programs occur in a source file, it is assumed that the programs are related to one another in that they will be CALLed or executed as functions from the others.

Nested Subprograms

It is also possible to create source files where GnuCOBOL programs are nested inside each other. Take for example these four GnuCOBOL programs:

```
IDENTIFICATION DIVISION.
PROGRAM-ID. PROG1.
...
IDENTIFICATION DIVISION.
PROGRAM-ID. PROG2.
...
IDENTIFICATION DIVISION.
PROGRAM-ID. PROG3.
...
END PROGRAM PROG3.
END PROGRAM PROG2.
IDENTIFICATION DIVISION.
PROGRAM-ID. PROG4.
...
END PROGRAM PROG4.
END PROGRAM PROG1.
```

Here we see that PROG2 is nested inside of PROG1 because there is no END PROGRAM marker separating them. This means that data items or files defined within PROG1 can be used within PROG2 simply by attaching the GLOBAL (see [GLOBAL], page 161) attribute to them back in PROG1 when they are defined.

Similarly, since there is no END PROGRAM marker separating PROG3 from PROG2, it is possible for PROG3 to access GLOBAL files and data items defined within PROG2. Since PROG2 is nested within PROG1, any GLOBAL resources defined within PROG1 will be available to PROG3 as well.

The two END PROGRAM markers for PROG3 and PROG2 (note their sequence) mean that PROG4 is nested within PROG1 only. It will not have access to any GLOBAL resources defined within either PROG2 or PROG3.

The END PROGRAM PROG1. marker, since it is the last line in the source file, is entirely optional.

11.3. Alternate Entry Points

Any subroutine may have multiple entry-points defined within it. This means the subroutine could be called either via a CALL 'program-id' or a CALL 'entry-point' statement. There may be any number of alternate entry-points defined within a subroutine.

Alternate entry-points provide multiple ways in which the same subroutine may be called; presumably, each entry-point will provide some different functionality to the calling program. For example, if you wished to write a subroutine that manipulates "student" records in a database, you might have the primary entry-point name retrieve a student record from the database, while

the alternate entry points Add-Student, Update-Student and Delete-Student could provide the alternate functions implied by their entry-point names.

The alternative to using multiple entry points in your subroutine, by the way, would be to include an additional argument to the primary (and only) entry point of the subroutine; this new argument might be named STUDENT-FUNCTION and might have values of 'FETCH', 'ADD', 'UPDATE' or 'DELETE'.

The primary entry-point for any subroutine is always the first executable statement following any DECLARATIVES (see [DECLARATIVES], page 218) in the procedure division. The name of that entry-point (the name that will be called) is the subroutine's PROGRAM-ID (see [IDENTIFICATION DIVISION], page 77).

An alternate entry point is added to a subroutine using the ENTRY statement (see [ENTRY], page 275).

When an alternate entry-point is called, execution within the subroutine will begin at the first executable statement following the ENTRY statement.

11.4. Dynamic vs Static Subprograms

Any subprogram may be either statically or dynamically loaded into memory.

A Static Subprogram is one which was in the same Compilation Unit (see [Compilation Unit], page 567) as the other program(s) which call it, therefore meaning that its executable object code is part of the same executable file as its calling program. The static subprogram was therefore loaded into memory as part of and at the same time as the calling program.

A Dynamic Subprogram is one whose executable object code exists as an executable file separate from that containing the calling program; these two programs were therefore each compiled in their own separate Compilation Group (see [Compilation Group], page 567). Dynamic subprograms are located and loaded into memory the first time they are executed. Dynamic subprograms may be unloaded from memory via the CANCEL statement (see [CANCEL], page 257), if desired.

GnuCOBOL subprograms may be created as either static or dynamic subprograms, as desired by the programmer.

To demonstrate, assume that a GnuCOBOL Main Program (whose code resides in the file M.cbl) will be calling three subprograms, named A, B and C (these are the PROGRAM-IDs of the three subprograms, and their source code may be found in the files A.cbl, B.cbl and C.cbl, respectively.

Here is how these four programs would be compiled if the three subprograms are to be static:

```
cobc -x M.cbl A.cbl B.cbl C.cbl
```

This command informs the compiler (cobc) that four programs are to be compiled (the first named on the command must always be the main program), and a single executable file is to be created (due to the -x switch).

Here is how the main program and the three subprograms could be compiled if the three subprograms are to be dynamic:

```
cobc -x M.cbl
cobc -m A.cbl B.cbl C.cbl
```

These commands will create an executable file for the main program (-x switch) and three separate dynamically-loadable libraries (see -m switch), one for each of the three subprograms. Had we wished, we could have created a single dynamically-loadable library containing all three subprograms by adding the -b switch to their compilation:

```
cobc -m -b A.cbl B.cbl C.cbl
```

Dynamically-loadable *libraries* are also known by the term dynamically-loadable *modules*. The two terms are synonymous.

Here are the rules about GnuCOBOL dynamically-loadable modules:

- 1. There may be multiple GnuCOBOL subprograms contained within a single dynamically-loadable library if the -b switch is used in addition to -m. If not, each subprogram will be compiled to a separate dynamically-loadable library.
- 2. Dynamically-loadable modules will be named xxxxxxxx.dll on a Windows system, xxxxxxxx.so on a Unix system or xxxxxxxxx.dylib on an OSX system, where xxxxxxxx exactly matches, including the usage of upper- and lower-case letters, the primary entry-point name (PROGRAM-ID or FUNCTION-ID) or an alternate entry point name defined via the ENTRY statement (see [ENTRY], page 275) of any one of the GnuCOBOL programs included in that module.
- 3. The first time any of the GnuCOBOL subprograms in a dynamically-loadable module are invoked, the entry-point referenced must be the one for which the .dll, .so or .dylib file is named.
- 4. When a dynamically-loadable module needs to be loaded (because it is not already in memory from a previous subprogram execution), the dynamically-loadable library will be sought in the same directory from which the main program was loaded. If it cannot be found there, each directory named in the PATH run-time environment variable (see [Run Time Environment Variables], page 584) will be searched. If it was not located in any of those directories, the library specified by the COB\_LIBRARY\_PATH run-time environment variable will be searched. Finally, if it still cannot be located, execution will be terminated with an error message (libcob: Cannot find module 'xxxxxxxxx').
- 5. Once the dynamically-loadable module has been successfully loaded, any of the entry-points contained within it are now available for reference.
- 6. Dynamically-loadable modules may be removed from memory via the CANCEL statement (see [CANCEL], page 257).
- 7. Once a dynamically-loadable module is actually loaded into memory, even if it is subsequently unloaded (via the CANCEL statement), its list of entry-points remain available to the GnuCOBOL run-time library and subsequent re-executions of any of those entry points will be able to bypass the search (rule #4) as well as the *first-execution rule* (rule #3).

Consult the documentation on the COB\_PRE\_LOAD run-time environment variable, COB\_PHYSICAL\_CANCEL run-time environment variable and COB\_LOAD\_CASE run-time environment variables (see [Run Time Environment Variables], page 584) for additional options when using dynamically-loadable modules.

11.5. Subprogram Execution Flow

When a subprogram is invoked, the flow of execution will differ slightly depending on whether the subprogram is a subroutine or a user-defined function.

11.5.1. Subroutine Execution Flow

When a subroutine is CALLed:

- 1. The calling program issues a statement of the form CALL 'entry-point' USING ... to transfer control to the subroutine.
- 2. The executable for the called program will be located and loaded into memory:
 - A. If it is a static subroutine, it will already be part of the executable program issuing the CALL (see [CALL], page 253).

- B. If it is a dynamic subroutine, the GnuCOBOL run-time system will check to see if a dynamically-loadable module containing the subprogram's entry point was already located. If it was, no further "location" activity is needed. If not, the dynamically-loadable module will be located (see [Locating Dynamically-Loadable Modules], page 606).
- C. Once the module has been located (if location was needed), it will be loaded into memory (if not already loaded).
- 3. Execution of the calling program is suspended and control will transfer to the called program, as follows:
 - A. If the PROGRAM-ID (see [IDENTIFICATION DIVISION], page 77) clause of the subprogram included the INITIAL clause, the program will be reinitialized back to its compile-time state. This will happen regardless of the INITIAL clause the first time the subprogram is executed.
 - B. Local-storage, if any, will be allocated and initialized.
 - C. Execution will begin at the first executable statement following the subprograms entry-point. The entry point will be either the first executable statement following any DECLARATIVES (see [DECLARATIVES], page 218) that might be present (if the subprogram was invoked using its primary entry-point name) or the first executable statement following the ENTRY statement (see [ENTRY], page 275) naming the entry-point specified on the CALL if the subprogram was invoked using an alternate entry point.
- 4. The flow of execution will then progress through the coding of the subprogram as it would with any other program.
- 5. If the subprogram issues a STOP statement (see [STOP], page 345) with the RUN option, program execution ceases and control returns to the operating system or whatever execution shell invoked the main program.
- 6. If the subprogram wishes to return control back to the calling program, it will do so using either the GOBACK statement (see [GOBACK], page 287) or the EXIT PROGRAM statement (see [EXIT], page 282). At this time:
 - A. If the subprograms procedure division header or ENTRY statement included a RETURNING, the value of the data item found on that clause is moved to the RETURN-CODE special register (see [Special Registers], page 227); this behaviour can be altered utilizing the CALL-CONVENTION (see [SPECIAL-NAMES], page 84) feature to leave RETURN-CODE unchanged.
 - B. Local-storage, if any, is de-allocated.
 - C. If the calling program included a RETURNING clause on the CALL statement that invoked the subprogram, the value of the RETURNING data item in the subroutine is moved to that data item. If there was no RETURNING specified in the subroutine, the value of the RETURN-CODE special register is moved to that data item.
 - D. Execution will resume back in the calling program with the first executable statement following the CALL that invoked the subprogram.

11.5.2. User-Defined Function Execution Flow

When a user-defined function is executed:

- 1. The object code for the called program (the user-defined function) will be located, as follows:
 - A. If it is a static user-defined function, it will already be part of the executable file containing the calling program.

- B. If it is a dynamic user-defined function, the GnuCOBOL run-time system will check to see if a dynamically-loadable module containing the function's entry point was already located. If it was, no further "location" activity is needed. If not, the dynamically-loadable module will be located (see [Locating Dynamically-Loadable Modules], page 606).
- C. Once the module has been located (if location was needed), it will be loaded into memory (if not already loaded).
- 2. Execution of the calling program is suspended and control will transfer to the called program, as follows:
 - A. Local-storage, if any, will be allocated and initialized.
 - B. Execution will begin with the first executable statement in the procedure division following any DECLARATIVES (see [DECLARATIVES], page 218) that might be present.
- 3. The flow of execution will then progress through the coding of the function as it would with any other program.
- 4. If the function issues a STOP statement (see [STOP], page 345) with the RUN option, program execution ceases and control returns to the operating system or whatever execution shell invoked the main program.
- 5. If the function wishes to return control back to the calling program, it will do so using either the GOBACK statement (see [GOBACK], page 287) or the EXIT FUNCTION statement (see [EXIT], page 282). At this time:
 - A. The value of the data item found on the user-defined functions PROCEDURE DIVISION RETURNING (see [PROCEDURE DIVISION RETURNING], page 216) clause is moved to the RETURN-CODE special register (see [Special Registers], page 227).
 - B. Local-storage, if any, is de-allocated.
 - C. Execution will resume back in the calling program at the point where the returned value of the function is needed. At that point, the value in the RETURN-CODE special register will be used for the function's value.

11.6. Sharing Data Between Calling and Called Programs

11.6.1. Subprogram Arguments

11.6.1.1. Calling Program Considerations

Data items defined in a calling program may be passed to either type of called program (subroutine or user-defined function) as arguments.

Arguments must be described in both the calling and called programs, and while they don't need to have the same names in both programs, they should be described in an identical manner with regard to the following characteristics:

- PICTURE (see [PICTURE], page 176) (including both type and length)
- SIGN (see [SIGN], page 443)
- SYNCRONIZED (see [SYNCRONIZED], page 193)
- USAGE (see [USAGE], page 198)

A subroutine may be passed a maximum of 251 arguments; if you build the GnuCOBOL software yourself from the distributed source, you CAN change this value by altering the defined value of COB\_MAX\_FIELD\_PARAMS in the call.h header file but also see 7.8.5.11 for more information. There is no built-in GnuCOBOL limit to how many arguments a user-defined function may be passed.

Whether or not changes made to an argument within a subroutine will be "visible" to the calling program depends on how the argument was passed. There are three ways in which arguments may be passed from a calling program to a subroutine, as defined by the use of optional BY clauses in the CALL (see [CALL], page 253) statement's list of arguments.

As an example, the following statement passes three arguments to a subroutine — each argument is passed differently.

```
CALL "subroutine" USING BY REFERENCE arg-1
BY CONTENT arg-2
BY VALUE arg-3
```

END-CALL

The three ways arguments are passed are as follows.

BY REFERENCE

When a subroutine argument is passed BY REFERENCE, the subroutine is passed the *address* of the *actual data item* being passed as an argument. The item may anything defined within the data division of the program. If the subroutine modifies the contents of this argument, the calling program will "see" the results of that change when the subroutine returns control. This is the default manner in which GnuCOBOL passes arguments to a subroutine, should no BY clauses be included on the CALL.

BY CONTENT

When a subroutine is passed an argument BY CONTENT, the subroutine is passed the address of a copy of the actual data being passed as an argument. The item may anything defined within the data division of the program. The copy is made each time the CALL statement is executed, immediately before the CALL actually takes place. If the subroutine modifies the contents of this argument, it will be the copy that is modified, not the original data item; the calling program will therefore not "see" the results of that change when the subroutine returns control.

BY VALUE

Passing a subroutine argument BY VALUE passes the *actual value* of the data being passed as an argument. The item may be any elementary binary numeric item defined within the data division of the program. If the subroutine modifies the contents of this argument, the calling program will not "see" the results of that change when the subroutine returns control.

The first two ways in which arguments may be passed (BY REFERENCE and BY CONTENT) are intended for use when a GnuCOBOL program is being called, while the first and third (BY REFERENCE and BY VALUE) are intended for use when a C program is being called. You *can* use BY VALUE arguments when calling GnuCOBOL subroutines, but remember that those arguments are limited to being a numeric binary data item.

Arguments to user-defined functions are always passed BY REFERENCE.

11.6.1.2. Called Program Considerations

When coding a GnuCOBOL subprogram (a subroutine or user-defined function), all arguments to the subprogram must be defined in the subprogram's linkage section.

These arguments must be explicitly included on the PROCEDURE DIVISION USING (see [PROCEDURE DIVISION USING], page 212) clause that lists the arguments in the sequence in which they will be passed to the subprogram.

These arguments described in the PROCEDURE DIVISION USING clause may each be defined as either BY REFERENCE, if the calling program is passing them either BY REFERENCE or BY CONTENT, or as BY VALUE if they are being passed BY VALUE.

By default, all arguments are assumed to be BY REFERENCE unless explicitly stated otherwise on the procedure division header.

Arguments to a user-defined function are always to be specified as BY REFERENCE (either explicitly or by not using any BY).

If the subprogram returns a value, the data item in which the value is returned must also be defined in the subprogram's linkage section, with a USAGE (see [USAGE], page 198) of BINARY-LONG SIGNED, or its equivalent.

11.6.2. GLOBAL Data Items

Another way in which a data item may be shared between a calling program (A) and a called program (B) is by defining the data item in the calling program and attaching the GLOBAL (see [GLOBAL], page 161) clause to it so that it may be used within the called program. In order for this to work, program B (the one called by program A) must be a nested subprogram within program A.

Here's a small example:

```
IDENTIFICATION DIVISION.

PROGRAM-ID. DemoGLOBAL.

ENVIRONMENT DIVISION.

DATA DIVISION.

WORKING-STORAGE SECTION.

O1 Arg GLOBAL PIC X(10).

PROCEDURE DIVISION.

000-Main.

MOVE ALL "X" TO Arg

CALL "DemoSub" END-CALL
```

```
DISPLAY "DemoGLOBAL: " Arg END-DISPLAY GOBACK
.
IDENTIFICATION DIVISION.
PROGRAM-ID. DemoSub.
PROCEDURE DIVISION.
000-Main.
MOVE ALL "*" TO Arg.
GOBACK
.
END PROGRAM DemoSub.
END PROGRAM DemoGLOBAL.
When the program runs, it produces the output:
DemoGLOBAL: **********
```

11.6.3. EXTERNAL Data Items

The final way in which a data item may be shared between a calling program (A) and a called program (B) is by defining the data item (with the same name) in both programs and attaching the EXTERNAL (see [EXTERNAL], page 156) clause to it (again, in both programs). This approach works regardless of whether the called program is nested within the calling program or not. It also works even if the two programs are compiled separately.

Here's a demonstration:

```
IDENTIFICATION DIVISION.
  PROGRAM-ID. DemoEXTERNAL.
  ENVIRONMENT DIVISION.
  DATA DIVISION.
  WORKING-STORAGE SECTION.
                                  PIC X(10).
  01 Arg EXTERNAL
  PROCEDURE DIVISION.
  000-Main.
      MOVE ALL "X" TO Arg
      CALL "DemoSub" END-CALL
      DISPLAY "DemoEXTERNAL: " Arg END-DISPLAY
      GOBACK
  END PROGRAM DemoEXTERNAL.
  IDENTIFICATION DIVISION.
  PROGRAM-ID. DemoSub.
  DATA DIVISION.
  WORKING-STORAGE SECTION.
  01 Arg EXTERNAL
                                   PIC X(10).
  PROCEDURE DIVISION.
  000-Main.
      MOVE ALL "*" TO Arg.
      GOBACK
  END PROGRAM DemoSub.
When the program runs, it produces the output:
  DemoEXTERNAL: ******
```

11.7. Recursive Subprograms

A subroutine may CALL itself, either directly or indirectly from another subroutine or user-defined function that it CALLs. Any subroutine that indulges in this sort of behaviour (called recursion) is called a *Recursive Subprogram*.

Any GnuCOBOL subroutine can be recursively invoked only if it is defined to the GnuCOBOL compiler as *being* a recursive subroutine. This is accomplished by adding the RECURSIVE attribute to its PROGRAM-ID (see [IDENTIFICATION DIVISION], page 77).

All User-defined functions are automatically capable of being executed recursively.

Here is an example of a main program (DEMOFACT) that calls both a subprogram (SUB) and a user-defined function (FUNC) to compute the factorial value of a number.

```
IDENTIFICATION DIVISION.
PROGRAM-ID. DEMOFACT.
ENVIRONMENT DIVISION.
CONFIGURATION SECTION.
REPOSITORY.
   FUNCTION RECURSIVEFUNC.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 Result USAGE BINARY-LONG.
01 Arg
             USAGE BINARY-LONG.
PROCEDURE DIVISION.
000-Main.
   MOVE 6 TO Arg
    CALL "RECURSIVESUB"
        USING BY CONTENT Arg
       RETURNING Result
    DISPLAY Arg "! = "
            Result
    DISPLAY Arg "! = "
            RECURSIVEFUNC (Arg)
    GOBACK
END PROGRAM DEMOFACT.
IDENTIFICATION DIVISION.
PROGRAM-ID. SUB RECURSIVE.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 Result USAGE BINARY-LONG.
01 Next-Arg USAGE BINARY-LONG.
01 Next-Result USAGE BINARY-LONG.
LINKAGE SECTION.
01 Arg
               USAGE BINARY-LONG.
PROCEDURE DIVISION USING Arg
              RETURNING Result.
000-Main.
   DISPLAY "Entering SUB"
            " Arg=" Arg
    IF Arg = 1
     MOVE 1 TO Result
     DISPLAY "Leaving SUB"
```

```
" Returning " Result
      ELSE
        SUBTRACT 1 FROM Arg
            GIVING Next-Arg
        CALL "SUB"
             USING BY CONTENT Next-Arg
             RETURNING Next-Result
        COMPUTE Result =
                Arg * Next-Result
        DISPLAY "Leaving SUB"
                " Returning "
                Result "=" Arg "*"
                Next-Result
      END-IF
      GOBACK
  END PROGRAM SUB.
  IDENTIFICATION DIVISION.
  FUNCTION-ID. FUNC.
  ENVIRONMENT DIVISION.
  CONFIGURATION SECTION.
  REPOSITORY.
      FUNCTION RECURSIVEFUNC.
  DATA DIVISION.
  WORKING-STORAGE SECTION.
  LINKAGE SECTION.
  01 Arg USAGE BINARY-LONG.
  01 Result USAGE BINARY-LONG
             SIGNED.
  PROCEDURE DIVISION USING Arg
               RETURNING Result.
  000-Main.
      DISPLAY "Entering FUNC"
             " Arg=" Arg
      IF Arg = 1
        MOVE 1 TO Result
      ELSE
        COMPUTE Result = Arg *
                FUNC(Arg - 1)
      END-IF
      DISPLAY "Leaving FUNC"
              " Returning " Result
      GOBACK
  END FUNCTION FUNC.
When DEMOFACT is executed, the output shown below is generated.
  E:\Programs\Demos>demofact
  Entering RECURSIVESUB Arg=+0000000006
  Entering RECURSIVESUB Arg=+0000000005
  Entering RECURSIVESUB Arg=+0000000004
```

```
Entering RECURSIVESUB Arg=+0000000003
Entering RECURSIVESUB Arg=+0000000002
Entering RECURSIVESUB Arg=+0000000001
Leaving RECURSIVESUB Returning +0000000001
Leaving RECURSIVESUB Returning +0000000002=+00000000002*+0000000001
Leaving RECURSIVESUB Returning +0000000006=+00000000003*+0000000002
Leaving RECURSIVESUB Returning +0000000024=+00000000004*+0000000006
Leaving RECURSIVESUB Returning +0000000120=+0000000005*+0000000024
Leaving RECURSIVESUB Returning +0000000720=+0000000006*+0000000120
+0000000006! = +0000000720
Entering RECURSIVEFUNC Arg=+0000000006
Entering RECURSIVEFUNC Arg=+0000000005
Entering RECURSIVEFUNC Arg=+0000000004
Entering RECURSIVEFUNC Arg=+0000000003
Entering RECURSIVEFUNC Arg=+0000000002
Entering RECURSIVEFUNC Arg=+0000000001
Leaving RECURSIVEFUNC Returning +0000000001
Leaving RECURSIVEFUNC Returning +0000000002
Leaving RECURSIVEFUNC Returning +0000000006
Leaving RECURSIVEFUNC Returning +0000000024
Leaving RECURSIVEFUNC Returning +0000000120
Leaving RECURSIVEFUNC Returning +0000000720
+0000000006! = +0000000720
```

11.8. Combining GnuCOBOL and C Programs

The upcoming sections deal the issues pertaining to calling C language programs from Gnu-COBOL programs, and vice versa. Two additional sections provide samples illustrating specifics as to how those issues are overcome in actual program code.

11.8.1. GnuCOBOL Run-Time Library Requirements

Like most other implementations of the COBOL language, GnuCOBOL utilizes a run-time library. When the first program executed in a given execution sequence is a GnuCOBOL program, any run-time library initialization will be performed by the compiled COBOL code in a manner that is transparent to the C-language programmer. If, however, a C program is the first to execute, the burden of performing GnuCOBOL run-time library initialization falls upon the C program. See [C Main Programs Calling GnuCOBOL Subprograms], page 617, for an example of how to do this.

11.8.2. String Allocation Differences Between GnuCOBOL and C

Both languages store strings as a fixed-length continuous sequence of characters.

COBOL stores these character sequences up to a specific quantity limit imposed by the PICTURE (see [PICTURE], page 176) clause of the data item. For example: 01 LastName PIC X(15)..

There is never an issue of exactly what the length of a string contained in a USAGE DISPLAY (see [USAGE], page 198) data item is — there are always exactly how ever many characters as were allowed for by the PICTURE clause. In the example above, LastName will always contain exactly fifteen characters; of course, there may be anywhere from 0 to 15 trailing SPACES as part of the current LastName value.

C actually has no "string" data type; it stores strings as an array of **char** data type items where each element of the array is a single character. Being an array, there is an upper limit to how many characters may be stored in a given "string". For example:

```
char lastName[15]; /* 15 chars: lastName[0] through lastName[14] */
```

C provides a robust set of string-manipulation functions to copy strings from one char array to another, search strings for certain characters, compare one char array to another, concatenate char arrays and so forth. To make these functions possible, it was necessary to be able to define the logical end of a string. C accomplishes this via the expectation that all strings (char arrays) will be terminated by a NULL character (x'00'). Of course, no one forces a programmer to do this, but if [s]he ever expects to use any of the C standard functions to manipulate that string they had better be null-terminating their strings!

So, GnuCOBOL programmers expecting to pass strings to or receive strings from C programs had best be prepared to deal with the null-termination issue, as follows:

- 1. Pass a quoted literal string from GnuCOBOL to C as a zero-delimited string literal (Z'string').
- 2. Pass alphanumeric (PIC X) or alphabetic (PIC A) data items to C subroutines by appending an ASCII NUL character (X'00') to them. For example, to pass the 15-character LastName data item described above to a C subroutine:

```
01 LastName-Arg-to-C PIC X(16).
...
MOVE FUNCTION CONCATENATE(LastName, X'00') TO LastName-Arg-to-C
```

And then pass LastName-Arg-to-C to the C subprogram!

3. When a COBOL program needs to process string data prepared by a C program, the embedded null character must be accounted for. This can easily be accomplished with an INSPECT statement (see [INSPECT], page 297) such as the following:

```
INSPECT Data-From-a-C-Program

REPLACING FIRST X'00' BY SPACE

CHARACTERS BY SPACE AFTER INITIAL X'00'
```

11.8.3. Matching C Data Types with GnuCOBOL USAGE's

Matching up GnuCOBOL numeric Usage's with their C language data type equivalents is possible via the following chart:

| COBOL BINARY-CHAR UNSIGNED BINARY-CHAR [SIGNED] BINARY-SHORT UNSIGNED | C unsigned char signed char unsigned unsigned int unsigned short |
|--|---|
| BINARY-SHORT [SIGNED] | unsigned short int int short short int signed int |
| BINARY-LONG UNSIGNED | signed short signed short int unsigned long unsigned long int |
| BINARY-LONG [SIGNED]
BINARY-INT | long long int signed long signed long int |
| BINARY-C-LONG [SIGNED]
BINARY-DOUBLE UNSIGNED | long unsigned long long unsigned long long int |
| BINARY-DOUBLE [SIGNED] BINARY-LONG-LONG COMPUTATIONAL-1 COMPUTATIONAL-2 N/A (no GnuCOBOL equivalent) | long long int
signed long long int
float
double
long double |

These sizes conform to the COBOL standard and the minimum sizes of the COBOL types are the same as the minimum sizes of the corresponding C data types. There's no official compatibility between them. Note that values in square braces '[]' are the defaults.

11.8.4. GnuCOBOL Main Programs CALLing C Subprograms

Here's a sample of a GnuCOBOL program that CALLs a C subprogram.

```
COBOL Calling Program
                                        C Called Program
IDENTIFICATION DIVISION.
                                       #include <stdio.h>
                                    int subc(char *arg1,
PROGRAM-ID. maincob.
DATA DIVISION.

WORKING-STORAGE SECTION.

01 Arg1 PIC X(7).

01 Arg2 PIC X(7).

01 Arg3 USAGE BINARY-LONG.

DIVISION.

printf("Arg1=%s\n",arg1);

printf("Arg2=%s\n",arg2);
                                                    unsigned long *arg3) {
    -Main. printf("Arg2=%s\n",arg2);
DISPLAY 'Starting maincob' printf("Arg3=%d\n",*arg3);
MOVE Z'Arg1' TO Arg1 arg1[0]='X';
    MOVE Z'Arg1' TO Arg1
MOVE Z'Arg2' TO Arg2
                                          arg2[0]='Y';
     MOVE 123456789 TO Arg3
                                            *arg3=987654321;
     CALL 'subc'
                                            return 2;
         USING BY CONTENT Arg1,
               BY REFERENCE Arg2,
```

```
BY REFERENCE Arg3
DISPLAY 'Back'
DISPLAY 'Arg1=' Arg1
DISPLAY 'Arg2=' Arg2
DISPLAY 'Arg3=' Arg3
DISPLAY 'Returned value='
RETURN-CODE
STOP RUN
```

The idea is to pass two string and one full-word unsigned arguments to the subprogram, have the subprogram print them out, change all three and pass a return code of 2 back to the caller. The caller will then re-display the three arguments (showing changes only to the two BY REFERENCE arguments), display the return code and halt.

While simple, these two programs illustrate the techniques required quite nicely.

Note how the COBOL program ensures that a null end-of-string terminator is present on both string arguments.

Since the C program is planning on making changes to all three arguments, it declares all three as pointers in the function header and references the third argument as a pointer in the function body. It actually had no choice for the two string (char array) arguments — they must be defined as pointers in the function even though the function code references them without the leading '\*' that normally signifies pointers.

These programs are compiled and executed as follows.

```
$ cobc -x maincob.cbl subc.c
$ maincob
Starting maincob
Starting subc
Arg1=Arg1
Arg2=Arg2
Arg3=123456789
Back
Arg1=Arg1
Arg2=Yrg2
Arg3=+0987654321
Returned value=+000000002
$
```

Remember that the null characters are actually in the GnuCOBOL Arg1 and Arg2 data items. They don't appear in the output, but they are there.

Did you notice the output showing the contents of Arg1 after the subroutine was called? Those contents were unchanged! The subroutine *definitely* changed that argument, but since the COBOL program passed that argument BY CONTENT, the change was made to a *copy* of the argument, not to the Arg1 data item itself.

11.8.5. C Main Programs Calling GnuCOBOL Subprograms

Now, the roles of the two languages in the previous section will be reversed, having a C main program execute a GnuCOBOL subprogram.

```
C Calling Program

GNU-COBOL Called Program

#include <libcob.h> /* COB RUN-TIME */

#include <stdio.h>

PROGRAM-ID. subcob.

int main (int argc, char **argv) {

int returnCode;

LINKAGE SECTION.
```

```
01 Arg1
char arg1[7] = "Arg1";
                                                          PIC X(7).
char arg2[7] = "Arg2";
                                            01 Arg2
01 Arg3
                                                          PIC X(7).
unsigned long arg3 = 123456789;
                                                          USAGE BINARY-LONG.
                                            PROCEDURE DIVISION USING
printf("Starting mainc...\n");
cob_init (argc, argv); /* COB RUN-TIME */
                                              BY VALUE
                                                            Arg1,
returnCode = subcob(arg1,arg2,&arg3);
                                              BY REFERENCE Arg2,
printf("Back\n");
                                               BY REFERENCE Arg3.
                                            000-Main.
printf("Arg1=%s\n",arg1);
printf("Arg2=%s\n",arg2);
                                                DISPLAY 'Starting cobsub.cbl'
                                                DISPLAY 'Arg1=' Arg1
printf("Arg3=%d\n",arg3);
                                                DISPLAY 'Arg2=' Arg2
printf("Returned value=%d\n",returnCode);
                                                DISPLAY 'Arg3=' Arg3
return returnCode;
                                                MOVE 'X' TO Arg1 (1:1)
                                                MOVE 'Y' TO Arg2 (1:1)
                                                MOVE 987654321 TO Arg3
                                                MOVE 2 TO RETURN-CODE
                                                GOBACK
```

Since the C program is the one that will execute first, before the GnuCOBOL subroutine, the burden of initializing the GnuCOBOL run-time environment lies with that C program; it will have to invoke the cob\_init function, which is part of the libcob library. The two required C statements are shown highlighted.

The arguments to the cob\_init routine are the argument count and value parameters passed to the main function when the program began execution. By passing them into the GnuCOBOL subprogram, it will be possible for that GnuCOBOL program to retrieve the command line or individual command-line arguments. If that won't be necessary, cob\_init(0,NULL); could be specified instead.

Since the C program wants to allow arg3 to be changed by the subprogram, it prefixes it with a '&' to force a CALL BY REFERENCE for that argument. Since arg1 and arg2 are strings (char arrays), they are automatically passed by reference.

Here's the output of the compilation process as well as the program's execution. The example assumes a Windows system with a GnuCOBOL build that uses the GNU C compiler on that system; the technique works equally well regardless of which C compiler and which operating system you're using.

```
C:\Users\Gary\Documents\Programs> cobc -S subcob.cbl
C:\Users\Gary\Documents\Programs> gcc mainc.c subcob.s -o mainc.exe -llibcob
C:\Users\Gary\Documents\Programs> mainc.exe
Starting mainc...
Starting cobsub.cbl
Arg1=Arg1
Arg2=Arg2
Arg3=+0123456789
Back
Arg1=Xrg1
Arg2=Yrg2
Arg3=987654321
Returned value=2
C:\Users\Gary\Documents\Programs>
```

Note that even though we told GnuCOBOL that the 1st argument was to be BY VALUE, it was treated as if it were BY REFERENCE anyway. String (char array) arguments passed from C callers to GnuCOBOL subprograms will be modifiable by the subprogram. It's best to pass a copy of such data if you want to ensure that the subprogram doesn't change it.

The third argument is different, however. Since it's not an array you have the choice of passing it either BY REFERENCE or BY VALUE.

End of Chapter 11 — Sub-Programming

12. Programming Style Suggestions

This chapter deals with a variety of stylistic issues that may be of interest to someone who is just starting out learning and using COBOL. Much of this chapter makes recommendations and suggestions for how to write your own programs. The sample programs in the *Sample Programs* document (see *Sample Programs*) were coded using almost all of these recommendations.

There's no particular order of importance to the topics presented here.

12.1. Marking Changes in Programs

Historically in the early 60's programs were first punched on to paper tape and by the mid 60's that was replaced almost totally, by punched cards although paper tape was still used by programmers for the odd few changes to their sources held on magnetic tape or disk as a portable paper tape punch could be put in your pocket. Now the problem with punched cards were there was 2,000 cards per box and that they could and did, get dropped. So, cc (column) 1 through 6 had the card sequence number in and that way if a box was dropped they could be feed in to a card sorter to be fixed. This was after the cards was cleaned up so that they were all in the same direction which one corner cut out helped.

In the late 70's cards was also on its way out to the point where P.C's started being used (and no they were not made by IBM), so these columns could be used for other purposes including cc 73 - 80 instead of indicating the 8 character program name which was the maximum size allowed on a IBM system.

For quite a while now (back to the late 1970's), the sequence number area' of a COBOL statement (columns 1-6) has come to be used as a change indicator area. Programmers would place a code in columns 1-6 of every line they changed in a program. The author works in a COBOL shop where change indicators of the form "xxmmyy" are required on every altered line of a program — "xx" is the initials of the programmer while "mmyy" are the month and two-digit year of the date the change was made. This is frequently accompanied by a comment block at or near the top of a COBOL program providing general documentation of what changes were made and what change indicator was used to mark that change.

The GCic sample program source listing (see Section "GCic" in *GnuCOBOL Sample Programs*) provides an excellent example of such documentation.

This technique of using columns 1-6 as a change indicator will *only* work if fixed source-record format is in effect.

Some COBOL shops prefer to use the eight-character Program Name Area (columns 73-80) as a change code area.

Marking changes becomes more of a challenge when free-format source code is in effect. Creating a top-of-program comment block to generically describe changes that have been made isn't difficult, even in free-form. What is difficult, however, is coming up with a scheme for per-statement mark up of changes that doesn't introduce a ridiculously excessive number of source lines to the program. I'm not sure there is a good answer to this problem (if a reader has one, please let me know). Generally, I've noticed that shops using free-format conventions for their COBOL source tend to stick with just the top-of-program comment block combined with minimal comment blocks sprinkled throughout the program noting areas that underwent major changes.

12.2. Data Item Coding and Naming Conventions

When programs get very large, it becomes more and more challenging to keep track of the data items that will be used in the program. Here, in no particular order of importance, are a variety of conventions that can simplify that problem.

Remember that the points described here are intended to make things easier for you, the programmer. No COBOL compiler cares one way or another whether any of these suggestions are followed.

- 1. Avoid the use of level 77 data items in new programs. Once (1968 and before) there were valid reasons for creating level-77 data items, but since the 1974 ANSI standard of COBOL there really hasn't been any reason why an elementary level-01 data item couldn't have been used instead of a level-77 item.
- 2. Allocate level-01 data items in alphabetical sequence in the program source wherever practical. This will make it vastly easier to locate the definitions of 01-level items in the program source without having to resort to a compilation cross-reference listing and/or text editor "find" command to locate them.
- 3. Consider prefixing data items with an indication of where in the program structure they were created. For example:
 - Start everything defined in the file section with "F-"
 - Start everything defined in working-storage with "WS-"
 - Start everything defined in local-storage with "LS-"
 - Start everything defined in the linkage section with "L-"
 - Start everything defined in the screen section with "S-"
 - Start everything defined in the report section with "R-"

A convention such as this makes it simple, when you're reviewing code in the procedure division, to know in which section of the data division you should look in when locating the detailed description of a data item. Once you're in the right division, coding convention #2 will assist in locating the data item definition.

4. Consider including a trailing descriptor of the nature of all data items in their names. The following chart presents a variety of such descriptors the author has encountered and used through the years.

| -ADDR | The data item contains all or a part of an Address (City-ADDR, State-ADDR, |
|-------|--|
| | Street-ADDR,) |

- -BOOL A level-88 data item (which only has the value TRUE or FALSE)
- -CD A *code* whose value denotes information content above and beyond that of the mere value itself. Some examples could be Error-CD, Status-CD, Billing-CD
- -CHR A data item containing a single character of data.
- -CONST A constant, specified as a level-78 data item, a level-01 item with the CONST attribute
- -DT The data item contains a complete or partial date (Birth-DT, Birth-Month-DT, Birth-Year-DT, ...)
- -DTTM A data item containing both a date and a time
- -FILE A file name. Note that these items would probably also have a "F-" prefix.
- -IDX A data item used as a table index (see section 12.3)

| -NM | All or a portion of a person's name. These could be extended to include business names, product names, etc. |
|------|---|
| -PTR | A data item whose USAGE is POINTER |
| -NUM | A generic numeric data item that doesn't fit into any of the other categories |
| -QTY | A count of something |
| -REC | An 01-level item defined in the FILE SECTION (constituting the layout of a record within a file). Note that these items would probably also have a "F-" prefix. |
| -SCR | The data item contains a complete or partial screen description (appropriate for SCREEN SECTION 01-level data items). |
| -SUB | A numeric item used as a table subscript (see section 12.3) |
| -TEL | All or part of a telephone number |
| -TM | The data item contains a complete or partial time value |
| -TXT | The data item contains generic alphanumeric text that doesn't fit into any of the other categories. |
| | |

The above is by no means an exhaustive list, but good programmers will use as few of these descriptors as possible as having too many defeats any benefits of such classification/documentation efforts.

5. Consider including an acronym to be inserted into the name of any data item defined directly or indirectly subordinate to an 01-level item, typically to be specified after any section-level tag, if you're using them. For example, consider the names used in the following structure:

```
O1 WS-File-Status-Message-TXT.

O5 FILLER

O5 WS-FSM-Status-CD

O5 FILLER

O5 WS-FSM-Msg-TXT

PIC X(13) VALUE 'Status Code: '.

PIC 9(2).

PIC X(11) VALUE ', Meaning: '.

PIC X(25).

PIC Y(25).

PIC 99 COMP.

PIC 99 COMP.
```

The "-FSM-" acronyms make it easier to locate the description of the 01-item the status code and message text items belong to.

12.3. Table Subscripting versus Table Indexing

The elements of a table may be referenced either using a subscript or an index. Syntactically, this is coded using parenthesis, as per the following three examples, all of which store the letter 'A' into the 17th occurrence of a data item named WS-Output-Image-TXT:

```
    MOVE 'A' TO WS-Output-Image-TXT (17)
    MOVE 17 TO WS-OI-SUB
        MOVE 'A' TO WS-Output-Image-TXT (WS-OI-SUB)
    SET WS-OI-IDX TO 17
        MOVE 'A' TO WS-Output-Image-TXT (WS-OI-IDX)
```

The 1st and 2nd examples are referred to as Subscripting while the 3rd is known as Indexing. The distinction is fairly simple.

Indexing is the process of referencing an element of a table utilizing a data item with an explicitly or implicitly defined USAGE (see [USAGE], page 198) of INDEX to select the desired occurrence, while . . .

Subscripting is the process of referencing an element of a table utilizing either a numeric constant or an unedited numeric data item to select the desired occurrence.

Various implementations of COBOL generate object code that is quite different in each of these three situations, and GnuCOBOL is no exception.

In general, table references such as example #1 (constant subscript) generate the smallest, simplest and fastest object code while table references such as example #2 (numeric data item subscript) generate the largest, most-complicated and slowest object code.

Table references such as example #3 (table indexing) generate object code that falls in the middle of the other two but is far closer in efficiency to example #1 than #2.

Some COBOL statements (SEARCH (see [SEARCH], page 327), SEARCH ALL (see [SEARCH ALL], page 328) and the table-based SORT (see [Table SORT], page 342)) require you to index the affected table and to utilize that index with those statements. With any other references to tables, the choice is left to the programmer as to which approach should be used. In general, follow these rules:

- 1. Use constant subscripts (example #1) wherever possible/practical.
- 2. If references to table elements are going to be performed many, many times (tens or hundreds of thousands of times or more) during program execution, you will probably see a noticeable reduction in program execution time if you use indexing versus subscripting.

It's impossible to perform any arithmetic operation against an index data item directly (other than a simple incrementation or decremental operation via the SET UP/DOWN statement (see [SET UP/DOWN], page 334)). Situations where any non-trivial computations are required to calculate the effective occurrence number for a table reference will require you to use a conventional unedited numeric data item as the receiving field for the calculation. That calculated value would then need to be saved into the index data item via a SET Index statement.

If you only need to use the computed occurrence number once, you might as well just use the computed occurrence number data item as a subscript. If, however, you will need to use a computed "subscript" many more times than once, the run-time overhead of converting that occurrence value to an index (via SET Index) will be worth the coding effort.

Whew!

If references to table elements are not going to be performed many, many times it probably won't make much difference whether you use indexing or subscripting.

If you are comfortable with the C programming language, you might find the following simple GnuCOBOL program useful in exploring the differences between subscripting and indexing:

```
IDENTIFICATION DIVISION.

PROGRAM-ID. SUBVSINDEX.

DATA DIVISION.

WORKING-STORAGE SECTION.

O1 WS-TABLE-SUB BINARY-LONG.

O1 WS-TABLE.

O5 WS-TABLE-ENTRY OCCURS 20 TIMES INDEXED BY WS-TABLE-IDX PIC X(1).

PROCEDURE DIVISION.

O00-Main SECTION.

E1. MOVE 'A' TO WS-TABLE-ENTRY (17)
```

```
E2. MOVE 17 TO WS-TABLE-SUB
MOVE 'A' TO WS-TABLE-ENTRY (WS-TABLE-SUB)
.
E3. SET WS-TABLE-IDX TO 17
MOVE 'A' TO WS-TABLE-ENTRY (WS-TABLE-SUB)
```

Compile this program as follows (the assumption is made that you are executing the cobc command from the directory in which the above program source code (subvsindex.cbl) exists.

```
cobc -C -save-temps subvsindex.cbl\
```

After this command is executed, the file subvsindex.c will contain the procedure division C code and subvsindex.c.1.h will contain the working-storage C code. Compare the generated C code for each of the three MOVE statements.

12.4. Copybook Naming Conventions and Usage

Since the intent of a copybook is to introduce COBOL code into a particular spot in a program via the COPY statement (see [COPY], page 59), it is always a good idea to prefix copybook names with a character sequence that identifies where in a program its contents are intended to be COPYed.

For example:

IDxxxxxxxx

Copybooks containing code intended for the identification division. These will be rare as you almost never encounter copied code in the identification division.

EDxxxxxxxx

Copybooks containing code intended for use in the environment division. These copybooks are generally used for predefined SPECIAL-NAMES (see [SPECIAL-NAMES], page 84) or FILE-CONTROL (see [INPUT-OUTPUT SECTION], page 94) syntax,

DDxxxxxxx

Copybooks that contain data definitions.

PDxxxxxxx

Copybooks that contain executable instructions.

12.5. PROCEDURE DIVISION Sections Versus Paragraphs

The issue of whether to use section and/or paragraph names (collectively referred to as procedure names) within the procedure division is one of near religious significance with many COBOL programmers.

COBOL programming standards used by many organizations that use the language generally call for procedure names to:

- 1. Contain a leading numeric component (for example: 2000-Update-Customer), AND...
- 2. Be defined in the procedure division in non-decreasing sequence of that numeric component.

When you are looking at or editing any large COBOL program that has been created with programming standards that include these two rules, it is always a simple thing to know whether a reference to a procedure is being made to code that exists before or after your current location in the program, simply by comparing the numeric component of the current procedure's name with the one in question.

Technically, GnuCOBOL does not require ANY procedure names be defined unless:

- 1. You are using the ALTER statement (see [ALTER], page 252) (the use of which should be avoided at all costs)
- 2. You are using a procedural PERFORM statement (see [Procedural PERFORM], page 311)
- 3. You are using a GO TO statement (see [GO TO], page 288)
- 4. You are using a MERGE statement (see [MERGE], page 302) with an OUTPUT PROCEDURE
- 5. You are using a SORT statement (see [SORT], page 339) with either (or both) an INPUT PROCEDURE or OUTPUT PROCEDURE
- 6. You are using DECLARATIVES (see [DECLARATIVES], page 218)

Since it is difficult to write any non-trivial COBOL program that uses none of the above, lets assume you will be including at least one section or paragraph in your GnuCOBOL programs.

I like to use procedure division paragraphs and sections as follows:

- 1. The very first procedure defined in the procedure division of my programs, assuming no DECLARATIVES (see [DECLARATIVES], page 218) are defined, will be a section named 000-Main. The declaration of this procedure will immediately follow the procedure division header (or END DECLARATIVES if DECLARATIVES are used).
- 2. Any procedures referenced by MERGE, PERFORM, or SORT statements will be defined as sections.
- 3. Any procedures referenced by GO TO statements will be defined as paragraphs, and those paragraphs will be defined in the same section as the GO TO statements that reference them. In other words, GO TO statements may not be used to transfer control to a point in a different section. This is *not* a GnuCOBOL rule this is my own personal programming practice intended to improve the readability and maintainability of my programs.
- 4. I always include a numeric prefix to all procedure names I define, for the reasons stated earlier
- 5. I do not use THRU on any MERGE, PERFORM or SORT statement unless the programming standards of the shop in which I am working require it. My reasoning for this is that it is too easy to accidentally introduce a new procedure into the scope of a THRU.

12.6. COMPUTE Versus ADD-SUBTRACT-MULTIPLY-DIVIDE

Over the years, there has been much debate over the efficiency and arithmetic accuracy of using the COMPUTE statement (see [COMPUTE], page 260) rather than the four basic arithmetic operation statements.

Here are the facts — draw your own conclusions as to which approach is more appropriate under which circumstances.

- 1. The COMPUTE statement supports exponentiation (via the '\*\*' operator) there is no equivalent basic arithmetic statement. Although you could simulate integral exponentiation (raising a value to the third power, for example) using MULTIPLY statements, and you may use the SQRT intrinsic function (see [SQRT], page 445) to find a square root, there's just no (easy) way to find the cube-root of a value without using the COMPUTE statement.
- 2. For non-trivial computations, COMPUTE statements "read" better. Take this, for example:

```
COMPUTE R = (A + B * C) / D
```

As compared to:

MULTIPLY B BY C GIVING TEMP ADD A TO TEMP

DIVIDE TEMP BY D GIVING R

For non-trivial computations, COMPUTE statements may execute faster than the equivalent chain of basic arithmetic statements. For example, the COMPUTE statement shown above executes about 25% faster on my computer using GnuCOBOL than does the MULTIPLY-ADD-DIVIDE sequence.

3. For trivial computations, on the other hand, I prefer the inherent readability of a statement such as this:

ADD 1 TO WSS-Input-Trans-QTY to this:

COMPUTE WS-Input-Trans-QTY = WS-Input-Trans-QTY + 1

End of Chapter 12 — Programming Style Suggestions

Appendix A - Glossary of Terms

Alphabetic Data Item

A data item whose PICTURE clause allows it to contain only upper- and/or lower-case letters. See [PICTURE], page 176.

Alphanumeric Data Item

A data item whose PICTURE clause allows it to contain absolutely any character whatsoever. See [PICTURE], page 176. Group items (see [Structured Data], page 13) are also implicitly considered to be alphanumeric data items.

Alphanumeric Literal

A string of characters enclosed within a pair of quotation marks ('"') or apostrophes ('''). See [Alphanumeric Literals], page 31.

Called Program

Another way to refer to a subprogram. Note that a called program may also be a calling program.

Calling Program

A program that executes a subprogram. Note that a calling program may also be a called program.

Collating Sequence

The sequence in which the characters that are acceptable to a computer are ordered for purposes of all types of sorting, merging, comparing, and processing. Gnu-COBOL programs may utilize standard character-set collating sequences (such as that defined by the ASCII or EBCDIC character sets) or programmer-defined custom sequences as specified in the OBJECT-COMPUTER paragraph (section 4.1.2) and defined in the SPECIAL-NAMES paragraph (section 4.1.4).

Compilation Group

The collection of all compilation units being compiled by a single execution of the GnuCOBOL compiler.

Compilation Unit

A single source file being compiled by the GnuCOBOL compiler. A compilation unit may contain one or more programs.

Control Break

An event that is triggered when a control field on an RWCS-generated report changes value. It is these events that trigger the generation of control heading and control footing groups.

Control Field

A field of data being presented within a detail group; as the various detail groups that comprise the report are presented, they are presumed to appear in sorted sequence of the control fields contained within them. As an example, a department-by-department sales report for a chain of stores would probably be sorted by store number and – within like store numbers – be further sorted by department number. The store number will undoubtedly serve as a control field for the report, allowing control heading groups to be presented before each sequence of detail groups for the same store and control footing groups to be presented after each such sequence.

Control Footing

A report group that appears immediately after one or more detail groups of an RWCS-generated report. Such are produced automatically as a result of a control

break. This type of group typically serves as a summary of the detail group(s) that precede it, as might be the case on a sales report for a chain of stores, where the detail groups documenting sales for each department (one department per detail group) from the same store might be followed by a control footing that provides a summation of the department-by-department sales for that store.

Control Heading

A report group that appears immediately before one or more detail groups of an RWCS-generated report. Such are produced automatically as a result of a control break. This type of group typically serves as an introduction to the detail group(s) that follow, as might be the case on a sales report for a chain of stores, where the detail groups documenting sales for each department (one department per detail group) from the same store might be preceded by a control heading that states the full name and location of the store.

Control Hierarchy

The natural hierarchy of control breaks within a RWCS-controlled report based upon the manner in which the data the report is being generated from is sorted.

Copybook

A segment of program code that may be utilized by multiple programs simply by having that program use the COPY statement to import that code into the program. Although similar to the "include" facility present in many other programming languages, the COBOL copybook mechanism is actually considerably more powerful. See [Copybooks], page 13, for a general discussion. See [COPY], page 59, for the specifics of the COPY statement.

Data Item

A contiguous area of storage within the memory space of a program that may be referenced, by name, in a COBOL program. Other programming languages use the term variable, property or attribute to describe the same concept. See [Structured Data, page 13.

Detail Group

A report group that contains the detailed data being presented for the report.

Detail Report

An RWCS-generated report to which at least one type of detail group is presented.

Division

A collection of zero, one, or more sections of paragraphs, called the division body, that are formed and combined in accordance with a specific set of rules. Each division consists of the division header and the related division body. There are four divisions in a GnuCOBOL program: Identification, Environment, Data, and Procedure (coded in that sequence). See [Program Structure], page 28.

Dynamic Subprogram

A subprogram whose executable object code is contained in a different executable file as its calling program. Dynamic subprograms are therefore loaded into memory as needed.

Elementary Item

A data item that isn't itself comprised of other data items. See [Structured Data], page 13.

Entry-point

A spot in the procedure division where a program may begin execution when it is executed from the operating system, invoked as a user-defined function or called by another program.

Every program has at least one entry-point — known as the primary entry-point — which corresponds to the first executable statement in the procedure division following the declaratives area, if any.

Additional entry-points may be defined via the ENTRY statement (see [ENTRY], page 275).

Entry-point Name

Every entry-point has a name. That name must be unique for all programs that comprise an executable program. Entry-point names are defined using a subroutine's PROGRAM-ID paragraph, a user-defined function's FUNCTION-ID paragraph or via ENTRY (see [ENTRY], page 275) statements coded in a subprogram's procedure division.

Executable File

The GnuCOBOL compiler can create operating-system appropriate files that may be executed directly from the operating system environment. On Windows systems, these will be .exe files whereas on UNIX systems they will have no specific extensions. The compiler's -x switch is used to create executable files. Only main programs should be compiled in this manner.

Execution Thread

The complete set of executable code that is run during the execution of a program. This includes the main program as well as all executed subprograms, including those that are both dynamically and statically loaded.

Figurative Constants

GnuCOBOL, like other COBOL implementations, supports a number of reserved words that may be used to represent a specific literal value. These are known as figurative constants. See [Figurative Constants], page 32, for more information.

Fixed Format Mode

A mode of the GnuCOBOL compiler's operation where source statements are constrained to meeting the pre-2002 standard of limiting COBOL statements to 80 columns, with various columns having limitations as to what sort of COBOL syntax could be specified in them. See [Format of Program Source Lines], page 25, for more information.

Free Format Mode

A mode of the GnuCOBOL compiler's operation where source statements are allowed to be as long as 255 characters, with no restrictions or requirements as to in which columns various syntax elements must appear. See [Format of Program Source Lines], page 25, for more information.

Group Item

A hierarchical data structure where the group item — itself a data item — actually consists of two or more other contiguously allocated data items. For example, Employee-Name could be a 35-character data item consisting of a 20-character Last-Name data item followed by a 14-character First-Name and a 1-character Middle-Initial. See [Structured Data], page 13.

Hexadecimal Alphanumeric Literal

These are alphanumeric literals whose character sequence is specified by hexadecimal value. These literals are formed by a quote- or apostrophe-delimited sequence of an even number of hexadecimal digits (upper- or lower-case), prefixed with the letter 'X' (also upper- or lower-case). For example, the character string "Demo" could be

specified as the hexadecimal alphanumeric literal X'44656D6F', assuming the ASCII character set. See [Alphanumeric Literals], page 31.

Hexadecimal Numeric Literal

A numeric literal whose value is specified by hexadecimal value. These literals are formed by a quote- or apostrophe-delimited sequence of from 1 to 16 hexadecimal digits (upper- or lower-case), prefixed with the letter 'H' (also upper- or lower-case). For example, the number 123456 could be specified as the hexadecimal numeric literal H'01E240'. See [Numeric Literals], page 31.

Identifiers

These are data items a COBOL program will be working with. The vast majority of identifiers are defined by the user (programmer) while a few are pre-defined by the GnuCOBOL compiler. Identifiers pre-defined by the compiler are referred to as special registers. Other programming languages generally refer to identifiers as "variables".

Imperative Statement

Either a statement that begins with a non decision-making verb and specifies an unconditional action to be taken or a conditional verb such as IF or EVALUATE, delimited by its explicit scope terminator (such as END-IF or END-EVALUATE). An imperative statement can consist of a sequence of imperative statements.

Intrinsic Function

A built-in routine that accepts arguments and returns a value; syntactically, these may be used most places where GnuCOBOL identifiers are valid. See [Intrinsic Functions], page 363, for documentation on all the GnuCOBOL intrinsic functions.

Level Number

A 1- or 2-digit number that indicates the hierarchical position of a data item in a group item or the special properties of a data description entry.

Level numbers in the range 1 through 49 indicate the position of a data item in the hierarchical structure of a logical record. Level numbers in the range 1 through 9 can be written either as a single digit or as a zero followed by the significant digit.

Level numbers 66, 77, 78 and 88 identify special properties of a data description entry.

Literal A generic term used for a constant value coded in a program that may be either a numeric literal or an alphanumeric literal.

Main program

A program that is executed directly from an operating system or shell event. Main programs are not executed from other programs (i.e. they are not called programs).

National Character set

A character set that supports symbols using other than the traditional Roman alphabet symbols used by the ASCII character set. Typically, such a character set uses a UTF-16 (i.e. 16 bits-per-character) encoding of the Unicode character set.

Support for national character sets in GnuCOBOL is currently only partially implemented, and the compile- and run-time effect of using the N symbol in a PICTURE (see [PICTURE], page 176) clause to define a field as containing national characters is the same as if X(2) had been coded, with the additional effect that such a field will qualify as a NATIONAL or NATIONAL-EDITED field on an INITIALIZE (see [INITIALIZE], page 292) statement.

Numeric Data Item

A data item whose PICTURE clause allows it to contain only the numeric digit characters 0-9 (signed or unsigned), or a data item whose PICTURE/USAGE combination allow it to contain actual binary numbers in integer, fixed-point, floating-point or packed-decimal format. Numeric data items are the only ones that may be used as table subscripts or as source arguments on arithmetic statements. PICTURE (see [PICTURE], page 176), or USAGE (see [USAGE], page 198).

Numeric Edited Data Item

An otherwise numeric data item whose PICTURE (see [PICTURE], page 176) clause also contains any of the editing symbols '\$', '\*', '+', ',', '-', '.', '/', '0' (zero), 'B', 'CR', 'DB' or 'Z'. Numeric edited data items are not eligible to serve as table subscripts or source arguments on arithmetic statements.

Numeric Literal

A numeric constant. See [Numeric Literals], page 31.

Page Footing

A report group that appears at the bottom of every page of an RWCS-generated report. Information typically found within such a report group might be:

- The date the report was generated
- The current page number of the report

Page Heading

A report group that appears at the top of every page of an RWCS-generated report. Information typically found within such a report group might be:

- A title for the report
- The date the report was generated
- The current page number of the report
- Column headings describing the fields within the detail group(s)

Primary Entry-Point

See entry-point.

Procedure

All executable code statements within a single procedure division paragraph or section.

Procedure name

A programmer-defined section or paragraph name in the procedure division assigned to a procedure. Procedure names serve as a means by which a statement may refer to the statements that follow the procedure name.

Program A GnuCOBOL main program or subprogram.

Qualification

The process of establishing a unique reference to a data item whose name is duplicated in a program. This takes the form of using the duplicated data name and the name of any of its parent data items, connected by OF or IN such that the combination of those two data names is unique within the program.

Record

A group item that is not part of a higher-level group item. See [Data Definition Principles], page 110. An elementary item with a level number of 01 can also be referred to as a record if its definition occurs in the file section, provided that its definition does not include the CONSTANT attribute. See [FILE-SECTION-Data-Item], page 116.

Report Footing

A report group that occurs only once in an RWCS-generated report — as the very last presented report group of the report. These typically serve as a visual indication that the report is finished.

Report Group

One or more consecutive lines on a report that serve a common informational purpose or function. For example, lines of text that are displayed at the top or bottom of every printed page of a report.

Report Heading

A report group that occurs only once in an RWCS-generated report — as the very first presented report group of the report. These typically serve as an introduction to the report.

Reserved Word

A word coded in a GnuCOBOL program without any quote or apostrophe characters around it (which would have transformed that sequence of characters into a literal string) which has a very specific meaning to the compiler. See [Language Reserved Words], page 9, for a general discussion of the concept. Appendix C for a complete list of GnuCOBOL reserved words.

Sentence An arbitrarily long sequence of statements terminated by a period.

Special Registers

Special data items that are automatically defined for your use by the GnuCOBOL compiler. See [Special Registers], page 227, for a complete list.

Statement

A single executable COBOL instruction. All statements start with a verb (DISPLAY, IF, MOVE, ...) which is followed by the operands and additional syntax elements that describe the actions to be performed.

Static Subprogram

A subprogram whose executable object code is part of the same executable file as its calling program. Static subprograms are therefore loaded into memory at the same time as their caller.

Subprogram

A program invoked directly by another program in such a manner that it may return control back to the other program, directly back to the point where the subprogram was invoked.

Subroutine

A subprogram executed from another via a GnuCOBOL CALL (see [CALL], page 253) statement (or the equivalent in whatever programming language that other program was written in).

Summary Report

An RWCS-generated report to which no detail groups are presented.

User-Defined Function

A subprogram written in GnuCOBOL that is executed in a syntactically-similar manner to that by which the various built-in intrinsic functions are executed.

User-Defined Names

Either the name of an identifier or a procedure in the program. GnuCOBOL limits user-defined names to a maximum of 31 characters taken from the set of numeric

digits, upper- and lower-case letters, hyphens and underscores. A user-defined name may neither begin nor end with a hyphen or underscore. User-defined names used as file names may additionally not begin with a digit although - unlike many other programming languages - user-defined names used as identifiers or procedure names may.

Verb The first reserved word of a COBOL statement.

Zero-Delimited Alphanumeric Literals

An alphanumeric literal prefixed with an upper- or lower-case 'Z' character — for example, Z'ABC'. These literals are one character longer than the value within apostrophes or quotes would make them appear. The extra character (the last character) will be a null character (comprised entirely of zero bits). These literals are ideal when defining or assigning values to alphanumeric data items that will be passed as arguments to a C subroutine. See [Alphanumeric Literals], page 31.

End of Appendix A — Glossary of Terms

Appendix B - Reserved Word Lists

See Appendix C for the complete lists of ALL reserved words of all types.

End of Appendix B — Reserved Word Lists

Appendix C1 - Grouped Word Lists by feature and function

The following is the complete list of ALL reserved words in the 31 December 2021 at 18:25 GMT. build of GnuCOBOL 3.2. Even though the functionality behind some of these words may not be implemented in this version of GnuCOBOL, none may be used as any user-defined name. This list includes ALL reserved, intrinsics, mnemonics and system and shows some 1100+ words in total. In addition there are the arithmetic and relational symbols see 1.3.15 as well as extra words that can be added and existing words removed by the use of the –std file content see the specific one used for each sub-set.

The following list of reserved words was extracted from cobc --list-reserved and shows the reserved words, an implementation

Please notice: This list is highly specific to the option -std=dialect and reserved word options (-freserved=word, -fno-reserved=word) in effect. You can get the list for a given dialect by calling cobc -std=dialect --list-reserved.

Common reserved words

| Reserved word | Implemented | Aliases |
|---------------------|-------------|---------|
| 3-D | Yes (C/S) | |
| ABSENT | Yes | |
| ACCEPT | Yes | |
| ACCESS | Yes | |
| ACTION | Yes (C/S) | |
| ACTIVE-CLASS | No | |
| ACTIVE-X | Yes (C/S) | |
| ACTUAL | Yes (C/S) | |
| ADD | Yes | |
| ADDRESS | Yes | |
| ADJUSTABLE-COLUMNS | Yes (C/S) | |
| ADVANCING | Yes | |
| AFTER | Yes | |
| ALIGNED | No | |
| ALIGNMENT | Yes (C/S) | |
| ALL | Yes | |
| ALLOCATE | Yes | |
| ALLOWING | Yes (C/S) | |
| ALPHABET | Yes | |
| ALPHABETIC | Yes | |
| ALPHABETIC-LOWER | Yes | |
| ALPHABETIC-UPPER | Yes | |
| ALPHANUMERIC | Yes | |
| ALPHANUMERIC-EDITED | Yes | |
| ALSO | Yes | |
| ALTER | Yes | |
| ALTERNATE | Yes | |
| AND | Yes | |
| ANY | Yes | |
| ANYCASE | No | |
| APPLY | Yes (C/S) | |
| ARE | Yes | |
| | | |

| | ** | |
|--------------------------|----------------------------|--------------------------|
| AREA | Yes | AREAS |
| AREAS | Yes | AREA |
| ARGUMENT-NUMBER | Yes | |
| ARGUMENT-VALUE | Yes | |
| ARITHMETIC | Yes (C/S) | |
| AS | Yes | |
| ASCENDING | Yes | |
| ASCII | Yes (C/S) | |
| ASSIGN | Yes | |
| AT | Yes | |
| ATTRIBUTE | Yes (C/S) | |
| ATTRIBUTES | Yes (C/S) | |
| AUTO | Yes (C/S) | AUTO-SKIP, AUTOTERMINATE |
| AUTO-DECIMAL | Yes (C/S) | |
| AUTO-SKIP | Yes | AUTO, AUTOTERMINATE |
| AUTO-SPIN | Yes (C/S) | |
| AUTOMATIC | Yes | |
| AUTOTERMINATE | Yes | AUTO, AUTO-SKIP |
| AWAY-FROM-ZERO | Yes (C/S) | |
| B-AND | No | |
| B-NOT | No | |
| B-OR | No | |
| B-XOR | No | |
| BACKGROUND-COLOR | Yes (C/S) | BACKGROUND-COLOUR |
| BACKGROUND-COLOUR | Yes | BACKGROUND-COLOR |
| BACKGROUND-HIGH | Yes | |
| BACKGROUND-LOW | Yes | |
| BACKGROUND-STANDARD | Yes | |
| BAR | Yes (C/S) | |
| BASED | Yes | |
| BEEP | Yes | BELL |
| BEFORE | Yes | DELL |
| | | DEED |
| BELL
BINARY | $\operatorname{Yes} (C/S)$ | BEEP |
| | Yes
V | |
| BINARY-C-LONG | Yes | |
| BINARY-CHAR | Yes | DIMARY LONG LONG |
| BINARY-DOUBLE | Yes | BINARY-LONG-LONG |
| BINARY-INT | Yes | BINARY-LONG |
| BINARY-LONG | Yes | BINARY-INT |
| BINARY-LONG-LONG | Yes | BINARY-DOUBLE |
| BINARY-SEQUENTIAL | Yes (C/S) | |
| BINARY-SHORT | Yes | |
| BIT | Yes | |
| BITMAP | Yes (C/S) | |
| BITMAP-END | Yes (C/S) | |
| BITMAP-HANDLE | Yes (C/S) | |
| BITMAP-NUMBER | Yes (C/S) | |
| BITMAP-START | Yes (C/S) | |
| BITMAP-TIMER | Yes (C/S) | |
| BITMAP-TRAILING | Yes (C/S) | |
| BITMAP-TRANSPARENT-COLOR | Yes (C/S) | |
| | | |

| BITMAP-WIDTH | Yes (C/S) | |
|-------------------|--|----------|
| BLANK | Yes | |
| BLINK | Yes (C/S) | |
| BLOCK | Yes | |
| BOOLEAN | No | |
| BOTTOM | Yes | |
| BOX | Yes (C/S) | |
| BOXED | Yes (C/S) | |
| BULK-ADDITION | Yes (C/S) | |
| BUSY | Yes (C/S) | |
| BUTTONS | Yes (C/S) | |
| ВУ | Yes | |
| BYTE-LENGTH | Yes (C/S) | |
| C | Yes (C/S) | |
| CALENDAR-FONT | Yes (C/S) | |
| CALL | Yes | |
| CANCEL | Yes | |
| CANCEL-BUTTON | Yes (C/S) | |
| CAPACITY | Yes (C/S) | |
| CARD-PUNCH | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| CARD-READER | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| CASSETTE | Yes (C/S) | |
| CCOL | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| CD | Yes | |
| CELL | (0.10) | CELLS |
| CELL-COLOR | Yes (C/S) | والماثار |
| CELL-DATA | Yes (C/S) | |
| CELL-FONT | Yes (C/S) | |
| CELL-PROTECTION | Yes (C/S) | |
| CELLS | ` ' ' | CELL |
| | | اللات |
| CENTER | Yes (C/S) | |
| CENTERED | Yes (C/S) | |
| CENTERED-HEADINGS | Yes (C/S) | |
| CENTURY-DATE | Yes (C/S) | |
| CF | Yes | |
| CH | Yes | |
| CHAIN | No | |
| CHAINING | Yes | |
| CHANGED | Yes (C/S) | |
| CHARACTER | Yes | |
| CHARACTERS | Yes | |
| CHECK-BOX | Yes (C/S) | |
| CLASS | Yes | |
| CLASS-ID | No | |
| CLASSIFICATION | Yes (C/S) | |
| CLEAR-SELECTION | Yes (C/S) | |
| CLINE | Yes (C/S) | |
| CLINES | Yes (C/S) | |
| CLOSE | Yes | |
| COBOL | Yes (C/S) | |
| CODE | Yes | |
| | | |

| CODE-SET | Yes | |
|-------------------|-----------|-----------------|
| COL | Yes | |
| COLLATING | Yes | |
| COLOR | Yes | |
| COLORS | Yes (C/S) | COLOURS |
| COLOURS | Yes | COLORS |
| COLS | Yes | |
| COLUMN | Yes | |
| COLUMN-COLOR | Yes (C/S) | |
| COLUMN-DIVIDERS | Yes (C/S) | |
| COLUMN-FONT | Yes (C/S) | |
| COLUMN-HEADINGS | Yes (C/S) | |
| COLUMN-PROTECTION | Yes (C/S) | |
| COLUMNS | Yes | |
| COMBO-BOX | Yes (C/S) | |
| COMMA | Yes | |
| COMMAND-LINE | Yes | |
| COMMIT | Yes | |
| COMMON | Yes | |
| COMMUNICATION | Yes | |
| COMP | Yes | COMPUTATIONAL |
| COMP-0 | Yes | COMPUTATIONAL-O |
| COMP-1 | Yes | COMPUTATIONAL-1 |
| COMP-2 | Yes | COMPUTATIONAL-2 |
| COMP-3 | Yes | COMPUTATIONAL-3 |
| COMP-4 | Yes | COMPUTATIONAL-4 |
| COMP-5 | Yes | COMPUTATIONAL-5 |
| COMP-6 | Yes | COMPUTATIONAL-6 |
| COMP-N | Yes | COMPUTATIONAL-N |
| COMP-X | Yes | COMPUTATIONAL-X |
| COMPUTATIONAL | Yes | COMP |
| COMPUTATIONAL-O | Yes | COMP-0 |
| COMPUTATIONAL-1 | Yes | COMP-1 |
| COMPUTATIONAL 1 | Yes | COMP-2 |
| COMPUTATIONAL 2 | Yes | COMP-3 |
| COMPUTATIONAL-4 | Yes | COMP-4 |
| COMPUTATIONAL-5 | Yes | COMP-5 |
| COMPUTATIONAL-6 | Yes | COMP-6 |
| COMPUTATIONAL-N | Yes | |
| | Yes | COMP-N |
| COMPUTATIONAL-X | Yes | COMP-X |
| COMPUTE | | |
| CONDITION | Yes | |
| CONFIGURATION | Yes | |
| CONSTANT | Yes | |
| CONTAINS | Yes | |
| CONTENT | Yes | |
| CONTINUE | Yes | |
| CONTROL | Yes | |
| CONTROLS | Yes | |
| CONVERSION | Yes (C/S) | |
| CONVERTING | Yes | |

| CODY | 37 | |
|-----------------------|--|---------------|
| COPY | Yes | |
| COPY-SELECTION | $\operatorname{Yes} (C/S)$ | |
| CORE-INDEX | Yes (C/S) | |
| CORR | Yes | CORRESPONDING |
| CORRESPONDING | Yes | CORR |
| COUNT | Yes | |
| CRT | Yes | |
| CRT-UNDER | Yes | |
| CSIZE | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| CURRENCY | Yes | |
| CURSOR | Yes | |
| CURSOR-COL | Yes (C/S) | |
| CURSOR-COLOR | Yes (C/S) | |
| CURSOR-FRAME-WIDTH | Yes (C/S) | |
| CURSOR-ROW | Yes (C/S) | |
| CURSOR-X | Yes (C/S) | |
| CURSOR-Y | Yes (C/S) | |
| CUSTOM-PRINT-TEMPLATE | Yes (C/S) | |
| CYCLE | Yes (C/S) | |
| CYL-INDEX | Yes (C/S) | |
| CYL-OVERFLOW | Yes (C/S) | |
| DASHED | Yes (C/S) | |
| DATA | Yes | |
| DATA-COLUMNS | Yes (C/S) | |
| DATA-POINTER | No | |
| DATA-TYPES | Yes (C/S) | |
| DATE | Yes | |
| DATE-ENTRY | Yes (C/S) | |
| DAY | Yes | |
| DAY-OF-WEEK | Yes | |
| DE | Yes | |
| DEBUGGING | Yes | |
| DECIMAL-POINT | Yes | |
| DECLARATIVES | Yes | |
| DEFAULT | Yes | |
| DEFAULT-BUTTON | Yes (C/S) | |
| DEFAULT-FONT | Yes | |
| DELETE | Yes | |
| DELIMITED | Yes | |
| DELIMITER | Yes | |
| DEPENDING | Yes | |
| DESCENDING | Yes | |
| DESTINATION | Yes | |
| DESTROY | Yes | |
| DETAIL | Yes | |
| DISABLE | Yes | |
| DISC | Yes (C/S) | |
| DISK | Yes (C/S) | |
| DISP | Yes (C/S) | |
| DISPLAY | Yes | |
| DISPLAY-COLUMNS | Yes (C/S) | |
| | | |

| DISPLAY-FORMAT | Yes (C/S) | |
|---------------------------|------------|-------------|
| DIVIDE | Yes | |
| DIVIDER-COLOR | Yes (C/S) | |
| DIVIDERS | Yes (C/S) | |
| DIVISION | Yes | |
| DOTDASH | Yes (C/S) | |
| DOTTED | Yes (C/S) | |
| DOUBLE | Yes | FLOAT-LONG |
| DOWN | Yes | |
| DRAG-COLOR | Yes (C/S) | |
| DROP-DOWN | Yes (C/S) | |
| DROP-LIST | Yes (C/S) | |
| DUPLICATES | Yes | |
| DYNAMIC | Yes | |
| EBCDIC | Yes (C/S) | |
| EC | Yes | |
| ECHO | Yes | |
| EGI | Yes | |
| ELEMENT | Yes (C/S) | |
| ELSE | Yes | |
| EMI | Yes | |
| EMPTY-CHECK | Yes | REQUIRED |
| ENABLE | Yes | TULIQUETULL |
| ENCODING | Yes (C/S) | |
| ENCRYPTION | Yes (C/S) | |
| END | Yes | |
| END-ACCEPT | Yes | |
| END-ADD | Yes | |
| END-CALL | Yes | |
| END-CHAIN | No | |
| END-COLOR | Yes (C/S) | |
| END-COMPUTE | Yes | |
| END-COMPOTE
END-DELETE | Yes | |
| END-DELETE
END-DISPLAY | Yes | |
| | | |
| END-DIVIDE | Yes
Yes | |
| END TE | Yes | |
| END_IGON | | |
| END-JSON | Yes (C/S) | |
| END-MODIFY | Yes (C/S) | |
| END-MULTIPLY | Yes
V | EOD |
| END-OF-PAGE | Yes | EOP |
| END-PERFORM | Yes | |
| END-READ | Yes | |
| END-RECEIVE | Yes | |
| END-RETURN | Yes | |
| END-REWRITE | Yes | |
| END-SEARCH | Yes | |
| END-START | Yes | |
| END-STRING | Yes | |
| END-SUBTRACT | Yes | |
| END-UNSTRING | Yes | |

| END-WRITE | Yes | |
|----------------------------|--|-------------|
| END-XML | Yes | |
| ENGRAVED | Yes (C/S) | |
| ENSURE-VISIBLE | Yes (C/S) | |
| ENTRY | Yes | |
| ENTRY-CONVENTION | Yes (C/S) | |
| ENTRY-FIELD | Yes (C/S) | |
| ENTRY-REASON | Yes (C/S) | |
| ENVIRONMENT | Yes | |
| ENVIRONMENT-NAME | Yes | |
| ENVIRONMENT-VALUE | Yes | |
| EO | No | |
| EOL | Yes (C/S) | |
| EOP | Yes | END-OF-PAGE |
| EOS | Yes (C/S) | |
| EQUAL | Yes | EQUALS |
| EQUALS | Yes | EQUAL |
| ERASE | Yes (C/S) | • |
| ERROR. | Yes | |
| ESCAPE | Yes | |
| ESCAPE-BUTTON | Yes (C/S) | |
| ESI | Yes | |
| EVALUATE | Yes | |
| EVENT | Yes | |
| EVENT-LIST | Yes (C/S) | |
| EVERY | Yes (C/S) | |
| EXCEPTION | Yes | |
| EXCEPTION EXCEPTION OBJECT | No | |
| | | |
| EXCEPTION-VALUE | $\operatorname{Yes} (C/S)$ | |
| EXCLUSIVE | Yes | |
| EXHIBIT | Yes | |
| EXIT | Yes | |
| EXPAND | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| EXPANDS | No (C/S) | |
| EXTEND | Yes | |
| EXTENDED-SEARCH | $\operatorname{Yes} (C/S)$ | |
| EXTERN | Yes (C/S) | |
| EXTERNAL | Yes | |
| EXTERNAL-FORM | Yes | |
| F | Yes (C/S) | |
| FACTORY | No | |
| FALSE | Yes | |
| FD | Yes | |
| FHFCD | Yes (C/S) | |
| FHKEYDEF | Yes (C/S) | |
| FILE | Yes | |
| FILE-CONTROL | Yes | |
| FILE-ID | Yes | |
| FILE-LIMIT | Yes (C/S) | |
| FILE-LIMITS | Yes (C/S) | |
| FILE-NAME | Yes (C/S) | |
| | • • • | |

| | T7 (Q (Q) | |
|--------------------|--|-------------------------|
| FILE-POS | Yes (C/S) | |
| FILL-COLOR | Yes (C/S) | |
| FILL-COLOR2 | Yes (C/S) | |
| FILL-PERCENT | Yes (C/S) | |
| FILLER | Yes | |
| FINAL | Yes | |
| FINISH-REASON | Yes (C/S) | |
| FIRST | Yes | |
| FIXED | Yes | |
| FIXED-FONT | Yes | |
| FIXED-WIDTH | Yes (C/S) | |
| FLAT | Yes (C/S) | |
| FLAT-BUTTONS | Yes (C/S) | |
| FLOAT | Yes | FLOAT-SHORT |
| FLOAT-BINARY-128 | No | |
| FLOAT-BINARY-32 | No | |
| FLOAT-BINARY-64 | No | |
| FLOAT-DECIMAL-16 | Yes | |
| FLOAT-DECIMAL-34 | Yes | |
| FLOAT-EXTENDED | No | |
| FLOAT-INFINITY | No | |
| FLOAT-LONG | Yes | DOUBLE |
| FLOAT-NOT-A-NUMBER | No (C/S) | |
| FLOAT-SHORT | Yes | FLOAT |
| FLOATING | Yes | |
| FONT | Yes | |
| FOOTING | Yes | |
| FOR | Yes | |
| FOREGROUND-COLOR | Yes (C/S) | FOREGROUND-COLOUR |
| FOREGROUND-COLOUR | Yes | FOREGROUND-COLOR |
| FOREVER | Yes (C/S) | 1 01/201/001/12 00/201/ |
| FORMAT | No | |
| FRAME | Yes (C/S) | |
| FRAMED | Yes (C/S) | |
| FREE | Yes | |
| FROM | Yes | |
| FULL | Yes (C/S) | LENGTH-CHECK |
| FULL-HEIGHT | Yes (C/S) | DENGIH OHLON |
| FUNCTION | Yes | |
| FUNCTION-ID | Yes | |
| FUNCTION-POINTER | No | |
| GENERATE | Yes | |
| GET | No | |
| GIVING | Yes | |
| GLOBAL | Yes | |
| | Yes | |
| GO PACK | | |
| GO-BACK | Yes (C/S)
Yes (C/S) | |
| GO-FORWARD | (/ / | |
| GO-HOME | Yes (C/S) | |
| GO-SEARCH | \mathbf{V}_{od} (\mathbf{C}/\mathbf{C}) | |
| GOBACK | Yes (C/S)
Yes | |

| GRAPHICAL | Yes (C/S) | |
|-----------------------|----------------------------|-------------|
| GREATER | Yes | |
| GRID | Yes (C/S) | |
| GROUP | Yes | |
| GROUP-USAGE | No | |
| GROUP-VALUE | Yes (C/S) | |
| HANDLE | Yes | |
| HAS-CHILDREN | Yes (C/S) | |
| HEADING | Yes | |
| HEADING-COLOR | Yes (C/S) | |
| HEADING-DIVIDER-COLOR | Yes (C/S) | |
| HEADING-FONT | Yes (C/S) | |
| HEAVY | Yes (C/S) | |
| HEIGHT-IN-CELLS | Yes (C/S) | |
| HIDDEN-DATA | Yes (C/S) | |
| HIGH-COLOR | Yes (C/S) | |
| HIGH-VALUE | Yes | HIGH-VALUES |
| HIGH-VALUES | Yes | HIGH-VALUE |
| HIGHLIGHT | Yes (C/S) | |
| HOT-TRACK | Yes (C/S) | |
| HSCROLL | Yes (C/S) | |
| HSCROLL-POS | Yes (C/S) | |
| I-0 | Yes | |
| I-O-CONTROL | Yes | |
| ICON | Yes (C/S) | |
| ID | Yes | |
| IDENTIFICATION | Yes | |
| IDENTIFIED | Yes | |
| IF | Yes | |
| IGNORE | Yes | |
| IGNORING | Yes (C/S) | |
| IMPLEMENTS | No (C/S) | |
| IN | Yes | |
| INDEPENDENT | Yes (C/S) | |
| INDEX | Yes | |
| INDEXED | Yes | |
| INDICATE | Yes | |
| INHERITS | No | |
| INITIAL | Yes | |
| INITIALISE | Yes | INITIALIZE |
| INITIALISED | Yes | INITIALIZED |
| INITIALIZE | Yes | INITIALISE |
| INITIALIZED | Yes (C/S) | INITIALISE |
| INITIATE | Yes | INTITALISED |
| INPUT | Yes | |
| | Yes | |
| INPUT-OUTPUT | | |
| INQUIRE | Yes (C/S) | |
| INSERT-ROWS | Yes (C/S) | |
| INSERTION-INDEX | $\operatorname{Yes} (C/S)$ | |
| INSPECT | Yes | |
| INTERFACE | No | |

| INTERFACE-ID | No | |
|------------------------|-----------|-----------|
| INTERMEDIATE | Yes (C/S) | |
| INTO | Yes | |
| INTRINSIC | Yes (C/S) | |
| INVALID | Yes | |
| INVOKE | No | |
| IS | Yes | |
| ITEM | Yes (C/S) | |
| ITEM-TEXT | Yes (C/S) | |
| ITEM-TO-ADD | Yes (C/S) | |
| ITEM-TO-DELETE | Yes (C/S) | |
| ITEM-TO-EMPTY | Yes (C/S) | |
| ITEM-VALUE | Yes (C/S) | |
| JSON | Yes | |
| JUST | Yes | JUSTIFIED |
| JUSTIFIED | Yes | JUST |
| KEPT | Yes | |
| KEY | Yes | |
| KEYBOARD | Yes (C/S) | |
| LABEL | Yes | |
| LABEL-OFFSET | Yes (C/S) | |
| LARGE-FONT | Yes | |
| LARGE-OFFSET | Yes (C/S) | |
| LAST | Yes | |
| LAST-ROW | Yes (C/S) | |
| LAYOUT-DATA | Yes (C/S) | |
| LAYOUT-MANAGER | Yes | |
| LC_ALL | No (C/S) | |
| LC_COLLATE | No (C/S) | |
| LC_CTYPE | No (C/S) | |
| LC_MESSAGES | No (C/S) | |
| LC_MONETARY | No (C/S) | |
| LC_NUMERIC | No (C/S) | |
| LC_TIME | No (C/S) | |
| LEADING | Yes | |
| LEADING-SHIFT | Yes (C/S) | |
| LEADING-SHIFT
LEAVE | Yes (C/S) | |
| LEFT | Yes | |
| LEFT-JUSTIFY | No | |
| LEFT-TEXT | Yes (C/S) | |
| LEFTLINE | Yes | |
| LENGTH | Yes | |
| LENGTH-CHECK | Yes | 17111 1 |
| | Yes | FULL |
| LESS | Yes | |
| LIKE | | |
| LIMIT | Yes | |
| LIMITS | Yes | |
| LINAGE | Yes | |
| LINAGE-COUNTER | Yes | |
| LINE | Yes | |
| LINE-COUNTER | Yes | |

| LINE-SEQUENTIAL | Yes (C/S) | |
|------------------------|--|------------|
| LINES | Yes | |
| LINES-AT-ROOT | Yes (C/S) | |
| LINKAGE | Yes | |
| LIST-BOX | Yes (C/S) | |
| LM-RESIZE | Yes | |
| LOC | Yes (C/S) | |
| LOCAL-STORAGE | Yes | |
| LOCALE | Yes | |
| LOCK | Yes | |
| LOCK-HOLDING | Yes (C/S) | |
| LONG-DATE | Yes (C/S) | |
| LOW-COLOR | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| LOW-VALUE | Yes | LOW-VALUES |
| LOW-VALUES | Yes | LOW-VALUE |
| LOWER | Yes (C/S) | LOW VILLOR |
| LOWERED | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| LOWLIGHT | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| MAGNETIC-TAPE | Yes (C/S) | |
| MANUAL | Yes | |
| | | |
| MASS-UPDATE | $\operatorname{Yes} (C/S)$ | |
| MASTER-INDEX | $\operatorname{Yes} (C/S)$ | |
| MAX-LINES | $\operatorname{Yes} (C/S)$ | |
| MAX-PROGRESS | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| MAX-TEXT | Yes (C/S) | |
| MAX-VAL | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| MEDIUM-FONT | Yes | |
| MEMORY | Yes (C/S) | |
| MENU | Yes | |
| MERGE | Yes | |
| MESSAGE | Yes | |
| METHOD | No | |
| METHOD-ID | No | |
| MIN-VAL | Yes (C/S) | |
| MINUS | Yes | |
| MODE | Yes | |
| MODIFY | Yes | |
| MODULES | Yes (C/S) | |
| MOVE | Yes | |
| MULTILINE | Yes (C/S) | |
| MULTIPLE | Yes | |
| MULTIPLY | Yes | |
| NAME | Yes (C/S) | |
| NAMED | Yes (C/S) | |
| NAMESPACE | Yes (C/S) | |
| NAMESPACE-PREFIX | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| NATIONAL | Yes | |
| NATIONAL-EDITED | Yes | |
| NATIVE | Yes | |
| NAVIGATE-URL | Yes (C/S) | |
| NEAREST-AWAY-FROM-ZERO | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| | (0/0) | |

| NEAREST-EVEN | Yes (C/S) | |
|---------------------|------------|-------|
| NEAREST-TOWARD-ZERO | Yes (C/S) | |
| NEGATIVE | Yes | |
| NESTED | Yes | |
| NEW | Yes | |
| NEXT | Yes | |
| NEXT-ITEM | Yes (C/S) | |
| NO | Yes | |
| NO-AUTO-DEFAULT | Yes (C/S) | |
| NO-AUTOSEL | Yes (C/S) | |
| NO-BOX | Yes (C/S) | |
| NO-DIVIDERS | Yes (C/S) | |
| NO-ECHO | Yes | |
| NO-F4 | Yes (C/S) | |
| NO-FOCUS | Yes (C/S) | |
| NO-GROUP-TAB | Yes (C/S) | |
| NO-KEY-LETTER | Yes (C/S) | |
| NO-SEARCH | Yes (C/S) | |
| NO-UPDOWN | Yes (C/S) | |
| NOMINAL | Yes (C/S) | |
| NONE | No (C/S) | |
| NONNUMERIC | Yes (C/S) | |
| NORMAL | Yes (C/S) | |
| NOT | Yes | |
| NOTAB | Yes (C/S) | |
| NOTHING | Yes | |
| NOTIFY | Yes (C/S) | |
| NOTIFY-CHANGE | Yes (C/S) | |
| NOTIFY-DBLCLICK | Yes (C/S) | |
| NOTIFY-SELCHANGE | Yes (C/S) | |
| NULL | Yes | NULLS |
| NULLS | Yes | NULL |
| NUM-COL-HEADINGS | Yes (C/S) | |
| NUM-ROWS | Yes (C/S) | |
| NUMBER | Yes | |
| NUMBERS | Yes | |
| NUMERIC | Yes | |
| NUMERIC-EDITED | Yes | |
| OBJECT | Yes | |
| OBJECT-COMPUTER | Yes | |
| OBJECT-REFERENCE | No | |
| OCCURS | Yes | |
| OF | Yes | |
| OFF | Yes | |
| OK-BUTTON | Yes (C/S) | |
| OMITTED | Yes | |
| ON | Yes | |
| ONLY | Yes | |
| OPEN | Yes | |
| OPTIONAL | Yes | |
| OPTIONS | Yes | |
| | _ 00 | |

| OR ORDER ORDER ORGANISATION ORGANISATION ORGANIZATION ORGANIZATION ORGANIZATION ORGANIZATION ORGANIZATION OTHER OTHER YES OTHERS YES OUTPUT YES OVERLAP- OVERLAP-TOP OVERLAP-TOP OVERLAP-TOP OVERLAP-TOP OVERLAP-TOP OVERLAP-TOP OVERLINE OVERRIDE No PACKED-DECIMAL YES PAGE PAGE PAGE YES PAGE-SETUP YES O(S) PARAGRAPH YES O(S) PARABNT YES O(S) PARABNT YES O(S) PARABNT YES O(S) PARASWORD YES O(S) PASSWORD YES O(S) PASSWORD YES O(S) PEPPOR PHYSICAL YES PEPNANENT YES PEPNANENT YES PERNANENT YES P | | ** | |
|--|-----------------|------------|---------------------|
| ORGANISATION Yes ORGANIZATION ORGANIZATION Yes ORGANISATION OTHER Yes ORGANISATION OTHERS Yes (C/S) OVERLAP OUTPUT Yes OVERLAP OVERLAP-LEFT Yes (C/S) OVERLAP-TOP OVERLAP-TOP Yes (C/S) OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLAP-TOP Yes (C/S) OVERLAP-TOP OVERLAP-TOP Yes C/S) | | | |
| ORGANIZATION Yes ORGANISATION OTHER Yes OTHERS Yes OTHERS Yes (C/S) OUTPUT Yes OVERLAP Yes OVERLAP-TOP OVERLAP-TOP OVERLAP-TOP Yes (C/S) OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLAP-TOP OVERLAP-TOP OVERLAP-TOP OVERLAP-TOP Yes C/S) PACE-SCAL Yes C/S) PAGE-SCAL Yes C/S) PAGE-SCAL Yes C/S) | | | 05 04 117 04 07 017 |
| OTHER Yes CC/S) OTHERS Yes CC/S) OUTPUT Yes OVERLAP-TOP OVERLAP-LEFT Yes CC/S) OVERLAP-TOP OVERLAP-TOP Yes CC/S) OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLINE Yes CC/S) OVERLINE Yes CC/S) OVERLINE Yes CC/S OVERLINE Yes CC/S OVERLINE Yes CC/S OVERLIAP-TOP OVERLAP-TOP OVERLAP-TOP OVERLAP-TOP PAGE PABOTA Yes PAGE | | | |
| OTHERS Yes OUTPTUT Yes OVERLAP-LOW Yes OVERLAP-LEFT Yes (C/S) OVERLAP-TOP OVERLAP-TOP Yes (C/S) OVERLAP-TOP OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-TOP OVERLINE Yes OVERLAP-TOP OVERLINE Yes C/S) OVERLINE Yes C/S OVERLIAP-TOP Yes C/S OVERLIAP-TOP OVERLAP-TOP OVERLAP-TOP OVERLAP-TOP Yes C/S PACCED Yes C/S PACKED Yes C/S PAG-CACHANA Yes Yes | | | URGANISATION |
| OUTPUT Yes OVERLAP-LEFT Yes (C/S) OVERLAP-TOP OVERLAP-TOP Yes (C/S) OVERLAP-TOP OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLAP-TOP Yes (C/S) PACH Yes (C/S) PACH Yes (C/S) PACH Yes (C/S) PAGE Yes< | | | |
| OVERLAP-LEFT Yes (C/S) OVERLAP-TOP OVERLAP-TOP Yes (C/S) OVERLAP-TOP OVERLAP-TOP Yes (C/S) OVERLAP-LEFT OVERLIDE No PADD OVERIDE No PAGE OVERIDE No PAGE OVERLAP-TOP Yes C/S) OVERLAP-TOP Yes C/S) OVERLAP-TOP Yes C/S) OVERLAP-TOP Yes C/S OVERLAP-TOP Yes C/S OVERLAP-TOP Yes C/S PACTOR No Yes PAGE Yes C/S PAGE Yes (C/S) Yes PAGE Yes (C/S) Yes PAGE - SCTUP Yes Yes PAGE - SCTUP Yes Yes PARSW Yes Yes PASSW | | ` ' ' | |
| OVERLAP-LEFT Yes (C/S) OVERLAP-TOP OVERLAP-TOP Yes (C/S) OVERLAP-TOP OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-TOP OVERLINE Yes OVERLAP-LEFT OVERLINE Yes OVERLAP-TOP OVERLAP-TOP Yes OVERLAP-TOP PASCAL Yes PERCHAP PAGE-CONTAIL Yes (C/S) PASCAL PAGE-SULT Yes Yes POPSTOR Yes PICTUP PICTURE Yes PICTURE PIXEL Yes (C/S) PIXELS PIXELS< | | | |
| OVERLAP-TOP Yes OVERLAP-LEFT OVERRIDE No PACKED-DECIMAL Yes PADDING Yes PAGE PAGE PAGE PAGE Yes PAGE | | | |
| OVERLINE Yes OVERRIDE No PACKED-DECIMAL Yes PADDING Yes PAGE Yes PAGE Yes PAGE Yes PAGE Yes PAGE Yes PAGE Yes PAGED Yes Yes (C/S) PAGED Yes PAGEO Yes PAGEO Yes PAGEO Yes PAGEO Yes PAGEO Yes PAGEO Yes PARSWORD Yes PASSWORD Yes PERMANET Yes | | ` ' ' | |
| OVERRIDE No PACKED-DECIMAL Yes PADDING Yes PAGE Yes PAGE Yes PAGE Yes PAGE Yes PAGE Yes PAGE Yes PAGED Yes Yes (C/S) PAGED Yes PAGE Yes PEFFORM Yes PEFFORM Yes PEFFORM Yes PHEFFORM <td></td> <td>` ' '</td> <td>OVERLAP-LEFT</td> | | ` ' ' | OVERLAP-LEFT |
| PACKED-DECIMAL Yes PADDING Yes PAGE Yes PAGE Yes PAGE Yes PAGE SETUP Yes (C/S) PAGED Yes (C/S) PARED Yes (C/S) PARENT Yes (C/S) PARSE Yes (C/S) PASSWORD Yes (C/S) PERFORM Yes PERMANENT Yes (C/S) PF Yes PH Yes PH Yes PHYSICAL Yes PIC Yes PHYSICAL Yes PIC Yes PHYSICAL Yes PIC Yes PIYSICAL Yes PIC Yes PIYSICAL Yes PIXEL Yes PIXEL Yes PIXEL Yes PIXEL Yes PIXELS Yes POP-UP Yes POSIT | | | |
| PADDING Yes PAGE Yes PAGE-COUNTER Yes PAGE-SETUP Yes (C/S) PAGED Yes (C/S) PARED Yes (C/S) PARENT Yes (C/S) PARSE Yes (C/S) PASSWORD Yes (C/S) PASSWORD Yes (C/S) PERFORM Yes PERMANENT Yes (C/S) PF Yes PH Yes PHYSICAL Yes PIC Yes PHYSICAL Yes PIC TURE Yes PIC PIXEL Yes PIC PIXEL Yes PIXEL Yes PLACEMENT Yes PLUS Yes POINTER Yes POP-UP Yes POS Yes POSITION Yes POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PREVIOUS Yes | | | |
| PAGE Yes PAGE-COUNTER Yes PAGE-SETUP Yes (C/S) PAGED Yes (C/S) PARAGRAPH Yes (C/S) PARSE Yes (C/S) PASCAL Yes (C/S) PASSWORD Yes (C/S) PEFFORM Yes PERMANENT Yes (C/S) PF Yes PH Yes PHYSICAL Yes PIC Yes PICTURE Yes PICTURE PIC PIXEL Yes (C/S) PIXELS Yes PIXELS Yes PIXELS PIXELS PIXEL Yes (C/S) PIXEL Yes POP-UP Yes (C/S) POS Yes POSITION Yes POSITION-SHIFT Yes (C/S) POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PREVIOUS Yes (C/S) PRIN | | | |
| PAGE-COUNTER Yes PAGED Yes (C/S) PAGED Yes (C/S) PARAGRAPH Yes (C/S) PARSE Yes (C/S) PARSE Yes (C/S) PASCAL Yes (C/S) PASSWORD Yes (C/S) PERFORM Yes PERMANENT Yes (C/S) PF Yes PH Yes PHYSICAL Yes PIC Yes PHYSICAL Yes PIC Yes PICTURE Yes PICTURE Yes PIXEL Yes (C/S) PIXEL Yes (C/S) PIXEL Yes PLACEMENT Yes POS Yes POP-UP Yes (C/S) POS Yes POS Yes POSITION Yes POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PRESENT Yes <td></td> <td></td> <td></td> | | | |
| PAGE-SETUP Yes (C/S) PAGED Yes (C/S) PARAGRAPH Yes (C/S) PARENT Yes (C/S) PARSE Yes (C/S) PASSWORD Yes (C/S) PASSWORD Yes (C/S) PERFORM Yes PERFORM Yes PERMANENT Yes (C/S) PF Yes PH Yes PH Yes PH Yes PICTURE PICTURE PIXEL Yes (C/S) PIXELS PIXEL PIXELS PIXEL PLUS Yes POINTER Yes POP-UP Yes (C/S) POS Yes POS Yes POSITION Yes POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PRESENT Yes PRINT-NO-PROMPT Yes (C/S) PRINTER-1 Yes (C/S) PRINTIN | | | |
| PAGED Yes (C/S) PARAGRAPH Yes (C/S) PARENT Yes (C/S) PARSE Yes (C/S) PASSAL Yes (C/S) PASSWORD Yes (C/S) PERFORM Yes PERFORM Yes PERMANENT Yes (C/S) PF Yes PH Yes PHYSICAL Yes PIC Yes PICTURE PIC PICTURE PIC PIXEL Yes PIXELS PIXELS PIXELS PIXELS PIXELS PIXEL PIXELS PIXEL PIXELS PIXEL PIXELS PIXEL PIXELS PIXEL PIXELS PIXELS PIXELS | | | |
| PARAGRAPH Yes (C/S) PARENT Yes (C/S) PARSE Yes (C/S) PASCAL Yes (C/S) PASSWORD Yes (C/S) PERFORM Yes PERMANENT Yes (C/S) PF Yes PH Yes PH Yes PH Yes PH Yes PIC Yes PICTURE PICTURE PICTURE Yes PIXEL Yes (C/S) PIXELS Yes PIXELS Yes PIXEL Yes (C/S) PIXEL Yes PIXEL Yes POINTER Yes POP-UP Yes (C/S) POS Yes POSITION Yes POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PRESENT Yes PRINT Yes PRINT-PROVIEW Yes | | | |
| PARENT Yes (C/S) PARSE Yes (C/S) PASCAL Yes (C/S) PASSWORD Yes (C/S) PERFORM Yes PERFORM Yes PERMANENT Yes (C/S) PF Yes PH Yes PH Yes PH Yes PIC Yes PICTURE PIC PIXEL Yes PIXELS Yes PIXELS Yes PIXEL Yes PIXEL Yes POS Yes POINTER Yes POS Yes POS Yes POSITION Yes POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PREVIOUS Yes PRINT Yes PRINT Yes PRINT-NO-PROMPT Yes PRINT-PREVIEW Yes PRIN | PAGED | | |
| PARSE Yes (C/S) PASCAL Yes (C/S) PASSWORD Yes (C/S) PERFORM Yes PERFORM Yes PERFORM Yes PERFORM Yes PERFORM Yes PH Yes PH Yes PH Yes PH Yes PIC Yes PICTURE PICTURE PICTURE PIC PIXEL Yes PIXELS PIXELS Yes PIXEL PEDIOL Yes Yes POSITION Yes Yes PRESIDION Yes Yes PRESIDION | PARAGRAPH | ` ' ' | |
| PASCAL Yes (C/S) PASSWORD Yes (C/S) PERFORM Yes PERMANENT Yes (C/S) PF Yes PH Yes PH Yes PHYSICAL Yes PIC Yes PICTURE PICTURE Yes PICTURE PIXEL Yes (C/S) PIXELS PIXELS Yes PIXEL PLACEMENT Yes (C/S) PIXEL PLUS Yes PIXEL POINTER Yes PIXEL POP-UP Yes (C/S) POS POS Yes Yes POSITION Yes Yes POSITION Yes Yes Yes PREFIXED No (C/S) PREFIXED PRESENT Yes PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT PRINT-NO-PROMPT Yes (C/S) PREVIOUS PRINTER Yes (C/S) PREVIOUS PRINTER | PARENT | | |
| PASSWORD Yes CC/S) PERFORM Yes PERFORM PERMANENT Yes PERFORM PF Yes Yes PH Yes Yes PH Yes PICTURE PIC Yes PICTURE PICTURE Yes PIXELS PIXEL Yes (C/S) PIXELS PIXELS Yes PIXEL PLACEMENT Yes (C/S) PIXEL PLOS Yes PIXEL POD-UP Yes (C/S) POSITION POS Yes Yes POSITION Yes Yes POSITIVE Yes Yes PREFIXED No (C/S) PRESENT PRESENT Yes Yes PRINT Yes (C/S) PRINT PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW PRINTER Yes (C/S) PRINTER PRINTER-1 Yes (C/S) PRINTING PRINTING Yes | PARSE | Yes (C/S) | |
| PERFORM Yes PERMANENT Yes (C/S) PF Yes PH Yes PHYSICAL Yes PIC Yes PICTURE PICTURE Yes PIC PIXEL Yes (C/S) PIXELS PIXELS Yes PIXEL PLOEMENT Yes (C/S) PIXEL PLUS Yes PIXEL POINTER Yes POS POS Yes POS POS TITION Yes POS POSITION-SHIFT Yes (C/S) POSITIVE Yes PRESENT PRESENT Yes PRESENT PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PASCAL | Yes (C/S) | |
| PERMANENT Yes PF Yes PH Yes PHYSICAL Yes PIC Yes PICTURE PICTURE Yes PIC PIXEL Yes (C/S) PIXELS PIXELS Yes PIXEL PIXEL Yes PIXEL POS Yes Yes POS Yes Yes POSITION Yes Yes POSITIVE Yes Yes PREFIXED No (C/S) PRESENT PRESENT Yes Yes PRINT Yes (C/S) PRINT PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes | PASSWORD | Yes (C/S) | |
| PF Yes PH Yes PHYSICAL Yes PIC Yes PICTURE PICTURE Yes PIC PIXEL Yes (C/S) PIXELS PIXELS Yes PIXEL PLUS Yes PIXEL PLUS Yes POS POINTER Yes POS POS Yes Yes POSITION Yes POSITIVE POSITIVE Yes PREFIXED PREFIXED No (C/S) PRESENT PRESENT Yes PRINT PREVIOUS Yes (C/S) PRINT PRINT Yes (C/S) PRINTER PRINT-PREVIEW Yes (C/S) PRINTER PRINTER-1 Yes (C/S) PRINTING PRIORITY Yes | PERFORM | Yes | |
| PH Yes PHYSICAL Yes PIC Yes PICTURE PICTURE Yes PIC PIXEL Yes (C/S) PIXELS PIXELS Yes PIXEL PIXELS Yes PIXEL PLOS Yes C/S) POINTER Yes Yes POS Yes Yes POSITION Yes Yes POSITIVE Yes Yes PREFIXED No (C/S) PRESENT PRESENT Yes Yes PRINT Yes (C/S) PRINT PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRINTING Yes PRIORITY Yes Yes | PERMANENT | Yes (C/S) | |
| PHYSICAL Yes PICTURE PIC Yes PICTURE PIXEL Yes (C/S) PIXELS PIXELS Yes PIXEL PIXELS Yes PIXEL PLUS Yes (C/S) PIXEL POINTER Yes POS POP-UP Yes (C/S) POS POSITION Yes POS POSITION-SHIFT Yes (C/S) POSITIVE Yes PREFIXED PRESENT Yes PRESENT PREVIOUS Yes (C/S) PRINT PRINT Yes (C/S) PRINT-NO-PROMPT PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PF | Yes | |
| PIC Yes PICTURE PIXEL Yes (C/S) PIXELS PIXELS Yes PIXELS PIXELS Yes PIXEL PLACEMENT Yes (C/S) PIXEL PLUS Yes POS POINTER Yes POS POP-UP Yes (C/S) POS POS Yes POS POSITION Yes POS POSITIVE Yes POS PREFIXED No (C/S) PRESENT PRESENT Yes PROS PRINT Yes (C/S) PRINT-NO-PROMPT PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PH | Yes | |
| PICTURE Yes PIC PIXEL Yes (C/S) PIXELS PIXELS Yes PIXEL PLACEMENT Yes (C/S) PIXEL PLUS Yes POS POINTER Yes POS POP-UP Yes (C/S) POS POS Yes POS POSITION Yes POS POSITIVE Yes POS PREFIXED No (C/S) PRESENT PRESENT Yes PREVIOUS PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PHYSICAL | Yes | |
| PIXEL Yes PIXELS PIXELS Yes PIXEL PLACEMENT Yes (C/S) PIXEL PLUS Yes POP-UP POP-UP Yes (C/S) POS POS Yes POSITION POSITION-SHIFT Yes (C/S) POSITIVE Yes PREFIXED PREFIXED No (C/S) PRESENT Yes PRINT PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PIC | Yes | PICTURE |
| PIXELS Yes PIXEL PLACEMENT Yes (C/S) PIXEL PLUS Yes POP-UP POP-UP Yes (C/S) POS POS Yes POSITION Yes POSITION-SHIFT Yes (C/S) POSITIVE PREFIXED No (C/S) PRESENT PRESENT Yes PRINT PRINT Yes (C/S) PRINT PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PICTURE | Yes | PIC |
| PLACEMENT Yes (C/S) PLUS Yes POINTER Yes POP-UP Yes (C/S) POS Yes POSITION Yes POSITIVE Yes (C/S) POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PIXEL | Yes (C/S) | PIXELS |
| PLUS Yes POINTER Yes POP-UP Yes (C/S) POS Yes POSITION Yes POSITIVE Yes (C/S) POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PIXELS | Yes | PIXEL |
| POINTER Yes POP-UP Yes (C/S) POS Yes POSITION Yes POSITIVE Yes (C/S) PREFIXED No (C/S) PRESENT Yes PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PLACEMENT | Yes (C/S) | |
| POP-UP Yes POS Yes POSITION Yes POSITION-SHIFT Yes (C/S) POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PLUS | Yes | |
| POS Yes POSITION Yes POSITION-SHIFT Yes (C/S) POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | POINTER | Yes | |
| POSITION Yes POSITION-SHIFT Yes (C/S) POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | POP-UP | Yes (C/S) | |
| POSITION-SHIFT Yes POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | POS | Yes | |
| POSITIVE Yes PREFIXED No (C/S) PRESENT Yes PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | POSITION | Yes | |
| PREFIXED No (C/S) PRESENT Yes PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | POSITION-SHIFT | Yes (C/S) | |
| PRESENT Yes PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | POSITIVE | Yes | |
| PREVIOUS Yes (C/S) PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PREFIXED | No (C/S) | |
| PRINT Yes (C/S) PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PRESENT | Yes | |
| PRINT-NO-PROMPT Yes (C/S) PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PREVIOUS | Yes (C/S) | |
| PRINT-PREVIEW Yes (C/S) PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PRINT | Yes (C/S) | |
| PRINTER Yes (C/S) PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PRINT-NO-PROMPT | Yes (C/S) | |
| PRINTER-1 Yes (C/S) PRINTING Yes PRIORITY Yes | PRINT-PREVIEW | Yes (C/S) | |
| PRINTING Yes PRIORITY Yes | PRINTER | Yes (C/S) | |
| PRIORITY Yes | PRINTER-1 | Yes (C/S) | |
| | PRINTING | Yes | |
| PROCEDURE Yes | PRIORITY | Yes | |
| | PROCEDURE | Yes | |

| PROCEDURE-POINTER | Yes | PROGRAM-POINTER |
|--------------------|--|-------------------|
| PROCEDURES | Yes | |
| PROCEED | Yes | |
| PROCESSING | Yes (C/S) | |
| PROGRAM | Yes | |
| PROGRAM-ID | Yes | |
| PROGRAM-POINTER | Yes | PROCEDURE-POINTER |
| PROGRESS | Yes (C/S) | |
| PROHIBITED | Yes (C/S) | |
| PROMPT | Yes | |
| PROPERTIES | Yes (C/S) | |
| PROPERTY | Yes | |
| PROTECTED | Yes (C/S) | |
| PROTOTYPE | No | |
| PURGE | Yes | |
| PUSH-BUTTON | Yes (C/S) | |
| QUERY-INDEX | Yes (C/S) | |
| QUEUE | Yes | |
| QUOTE | Yes | QUOTES |
| QUOTES | Yes | QUOTE |
| RADIO-BUTTON | Yes (C/S) | QOUL |
| RAISE | Yes | |
| RAISED | Yes (C/S) | |
| RAISING | No | |
| RANDOM | Yes | |
| RD | Yes | |
| READ | Yes | |
| READ-ONLY | Yes (C/S) | |
| | ` ' ' | |
| READERS
RECEIVE | Yes (C/S)
Yes | |
| | Yes | |
| RECORD | | |
| RECORD OVEREI OU | $\operatorname{Yes} (C/S)$ | |
| RECORD-OVERFLOW | $\operatorname{Yes} (C/S)$ | |
| RECORD-TO-ADD | Yes (C/S) | |
| RECORD-TO-DELETE | Yes (C/S) | |
| RECORDING | Yes | |
| RECORDS | Yes | |
| RECURSIVE | Yes (C/S) | |
| REDEFINES | Yes | |
| REEL | Yes | |
| REFERENCE | Yes | |
| REFERENCES | Yes | |
| REFRESH | $\operatorname{Yes} (C/S)$ | |
| REGION-COLOR | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| RELATION | No (C/S) | |
| RELATIVE | Yes | |
| RELEASE | Yes | |
| REMAINDER | Yes | |
| REMOVAL | Yes | |
| RENAMES | Yes | |
| REORG-CRITERIA | Yes (C/S) | |

| REPLACE | Yes | |
|-------------------|-----------|-------------|
| REPLACING | Yes | |
| REPORT | Yes | |
| REPORTING | Yes | |
| REPORTS | Yes | |
| REPOSITORY | Yes | |
| REQUIRED | Yes (C/S) | EMPTY-CHECK |
| REREAD | Yes (C/S) | |
| RERUN | Yes (C/S) | |
| RESERVE | Yes | |
| RESET | Yes | |
| RESET-GRID | Yes (C/S) | |
| RESET-LIST | Yes (C/S) | |
| RESET-TABS | Yes (C/S) | |
| RESUME | No | |
| RETRY | Yes | |
| RETURN | Yes | |
| RETURNING | Yes | |
| REVERSE | Yes | |
| REVERSE-VIDEO | Yes (C/S) | |
| REVERSED | Yes | |
| REWIND | Yes | |
| REWRITE | Yes | |
| RF | Yes | |
| RH | Yes | |
| RIGHT | Yes | |
| RIGHT-ALIGN | Yes (C/S) | |
| RIGHT-JUSTIFY | No | |
| RIMMED | Yes (C/S) | |
| ROLLBACK | Yes | |
| ROUNDED | Yes | |
| ROUNDING | Yes (C/S) | |
| ROW-COLOR | Yes (C/S) | |
| ROW-COLOR-PATTERN | Yes (C/S) | |
| ROW-DIVIDERS | Yes (C/S) | |
| ROW-FONT | Yes (C/S) | |
| ROW-HEADINGS | Yes (C/S) | |
| ROW-PROTECTION | Yes (C/S) | |
| RUN | Yes | |
| S | Yes (C/S) | |
| SAME | Yes | |
| SAVE-AS | Yes (C/S) | |
| SAVE-AS-NO-PROMPT | Yes (C/S) | |
| SCREEN | Yes | |
| SCROLL | Yes (C/S) | |
| SCROLL-BAR | Yes (C/S) | |
| SD | Yes | |
| SEARCH | Yes | |
| SEARCH-OPTIONS | Yes (C/S) | |
| SEARCH-TEXT | Yes (C/S) | |
| SECONDS | Yes (C/S) | |
| | ` ' ' | |

| SECTION | Yes | |
|------------------|-----------|--------|
| SECURE | Yes (C/S) | |
| SEGMENT | Yes | |
| SEGMENT-LIMIT | Yes | |
| SELECT | Yes | |
| SELECT-ALL | Yes (C/S) | |
| SELECTION-INDEX | Yes (C/S) | |
| SELECTION-TEXT | Yes (C/S) | |
| SELF | No | |
| SELF-ACT | Yes (C/S) | |
| SEND | Yes | |
| | | |
| SENTENCE | Yes | |
| SEPARATE | Yes | |
| SEPARATION | Yes (C/S) | |
| SEQUENCE | Yes | |
| SEQUENTIAL | Yes | |
| SET | Yes | |
| SHADING | Yes (C/S) | |
| SHADOW | Yes (C/S) | |
| SHARING | Yes | |
| SHORT-DATE | Yes (C/S) | |
| SHOW-LINES | Yes (C/S) | |
| SHOW-NONE | Yes (C/S) | |
| SHOW-SEL-ALWAYS | Yes (C/S) | |
| SIGN | Yes | |
| SIGNED | Yes | |
| | Yes | |
| SIGNED LONG | Yes | |
| SIGNED-LONG | | |
| SIGNED-SHORT | Yes | |
| SIZE | Yes | |
| SMALL-FONT | Yes | |
| SORT | Yes | |
| SORT-MERGE | Yes | |
| SORT-ORDER | Yes (C/S) | |
| SOURCE | Yes | |
| SOURCE-COMPUTER | Yes | |
| SOURCES | No | |
| SPACE | Yes | SPACES |
| SPACE-FILL | No | |
| SPACES | Yes | SPACE |
| SPECIAL-NAMES | Yes | |
| SPINNER | Yes (C/S) | |
| SQUARE | Yes (C/S) | |
| STANDARD | Yes | |
| | Yes | |
| STANDARD O | | |
| STANDARD-2 | Yes (C(G) | |
| STANDARD-BINARY | Yes (C/S) | |
| STANDARD-DECIMAL | Yes (C/S) | |
| START | Yes | |
| START-X | Yes (C/S) | |
| START-Y | Yes (C/S) | |
| | | |

| | NT (0 /0) | |
|----------------------------|----------------------------|----------------------------|
| STATEMENT | No (C/S) | |
| STATIC | Yes (C/S) | |
| STATIC-LIST | Yes (C/S) | |
| STATUS | Yes | |
| STATUS-BAR | Yes (C/S) | |
| STATUS-TEXT | Yes (C/S) | |
| STDCALL | Yes (C/S) | |
| STEP | Yes (C/S) | |
| STOP | Yes | |
| STRING | Yes | |
| STRONG | No (C/S) | |
| STYLE | Yes (C/S) | |
| SUB-QUEUE-1 | Yes | |
| SUB-QUEUE-2 | Yes | |
| SUB-QUEUE-3 | Yes | |
| SUBTRACT | Yes | |
| SUBWINDOW | Yes | |
| SUM | Yes | |
| SUPER | No | |
| SUPPRESS | Yes | |
| SYMBOL | No (C/S) | |
| SYMBOLIC | Yes | |
| SYNC | Yes | SYNCHRONISED, SYNCHRONIZED |
| SYNCHRONISED | Yes | SYNC, SYNCHRONIZED |
| SYNCHRONIZED | Yes | SYNC, SYNCHRONISED |
| SYSTEM-DEFAULT | Yes | Sino, Sinomonists |
| SYSTEM-INFO | Yes (C/S) | |
| SYSTEM-OFFSET | Yes | |
| TAB | Yes (C/S) | |
| TAB-TO-ADD | Yes (C/S) | |
| TAB-TO-DELETE | Yes (C/S) | |
| TABLE | Yes | |
| TALLYING | Yes | |
| TAPE | | |
| | Yes (C/S)
Yes (C/S) | |
| TEMPORARY
TERMINAL-INFO | | |
| TERMINATE | Yes (C/S)
Yes | |
| TERMINATION-VALUE | | |
| | $\operatorname{Yes} (C/S)$ | |
| TEST | Yes | |
| TEXT | Yes | |
| THAN | Yes | |
| THEN | Yes | |
| THREAD | Yes | |
| THREADS | Yes | |
| THROUGH | Yes | THRU |
| THRU | Yes | THROUGH |
| THUMB-POSITION | Yes (C/S) | |
| TILED-HEADINGS | Yes (C/S) | |
| TIME | Yes | |
| TIME-OUT | Yes (C/S) | TIMEOUT |
| TIMEOUT | Yes | TIME-OUT |
| | | |

| TIMES | Yes |
|------------------|-------------|
| TITLE | Yes (C/S) |
| TITLE-POSITION | Yes (C/S) |
| TO | Yes |
| TOP | Yes |
| TOWARD-GREATER | Yes (C/S) |
| TOWARD-LESSER | Yes (C/S) |
| TRACK | Yes (C/S) |
| TRACK-AREA | Yes (C/S) |
| TRACK-LIMIT | Yes (C/S) |
| TRACKS | Yes (C/S) |
| TRADITIONAL-FONT | Yes |
| TRAILING | Yes |
| TRAILING-SHIFT | Yes (C/S) |
| TRAILING-SIGN | No |
| TRANSFORM | Yes |
| TRANSPARENT | Yes (C/S) |
| TREE-VIEW | Yes (C/S) |
| TRUE | Yes |
| TRUNCATION | Yes (C/S) |
| TYPE | Yes |
| TYPEDEF | No |
| U | Yes (C/S) |
| UCS-4 | Yes (C/S) |
| UNBOUNDED | Yes (C/S) |
| UNDERLINE | Yes (C/S) |
| UNFRAMED | Yes (C/S) |
| UNIT | Yes |
| UNIVERSAL | No |
| UNLOCK | Yes |
| UNSIGNED | Yes |
| UNSIGNED-INT | Yes |
| UNSIGNED INT | Yes |
| UNSIGNED-SHORT | Yes |
| | |
| UNSORTED | Yes (C/S) |
| UNSTRING | Yes
Yes |
| UNTIL | |
| UP | Yes |
| UPDATE | Yes |
| UPDATERS | Yes (C/S) |
| UPON | Yes |
| UPPER | Yes (C/S) |
| USAGE | Yes |
| USE | Yes (C/C) |
| USE-ALT | Yes (C/S) |
| USE-RETURN | Yes (C/S) |
| USE-TAB | Yes (C/S) |
| USER | Yes (C/S) |
| USER-DEFAULT | Yes |
| USING | Yes (C/S) |
| UTF-16 | Yes (C/S) |

| | TT (0 (0) | |
|-----------------|--|---------------|
| UTF-8 | Yes (C/S) | |
| V | Yes (C/S) | |
| VAL-STATUS | No | |
| VALID | No | |
| VALIDATE | Yes | |
| VALIDATE-STATUS | No | |
| VALIDATING | Yes (C/S) | |
| VALUE | Yes | VALUES |
| VALUE-FORMAT | Yes (C/S) | |
| VALUES | Yes | VALUE |
| VARIABLE | Yes (C/S) | |
| VARIANT | Yes | |
| VARYING | Yes | |
| VERTICAL | Yes (C/S) | |
| VERY-HEAVY | Yes (C/S) | |
| VIRTUAL-WIDTH | Yes (C/S) | |
| VOLATILE | Yes | |
| VPADDING | Yes (C/S) | |
| VSCROLL | Yes (C/S) | |
| VSCROLL-BAR | Yes (C/S) | |
| VSCROLL-POS | Yes (C/S) | |
| VTOP | Yes (C/S) | |
| WAIT | Yes | |
| WEB-BROWSER | Yes (C/S) | |
| WHEN | Yes | |
| WIDTH | Yes (C/S) | |
| WIDTH-IN-CELLS | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| WINDOW | Yes | |
| WITH | Yes | |
| WORDS | Yes | |
| WORKING-STORAGE | Yes | |
| | | |
| WRAP | $\begin{array}{c} { m Yes} \ { m (C/S)} \\ { m Yes} \end{array}$ | |
| WRITE | | |
| WRITE-ONLY | $\operatorname{Yes} (C/S)$ | |
| WRITE-VERIFY | $\operatorname{Yes} (C/S)$ | |
| WRITERS | $\operatorname{Yes} (C/S)$ | |
| X | $\operatorname{Yes}\left(\mathrm{C/S}\right)$ | |
| XML | Yes | |
| XML-DECLARATION | Yes (C/S) | |
| Υ | Yes (C/S) | |
| YYYYDDD | Yes (C/S) | |
| YYYYMMDD | Yes (C/S) | |
| ZERO | Yes | ZEROES, ZEROS |
| ZERO-FILL | No (C/S) | |
| ZEROES | Yes | ZERO, ZEROS |
| ZEROS | Yes | ZERO, ZEROES |
| | | |

Extra (obsolete) context sensitive words

AUTHOR, DATE-COMPILED, DATE-MODIFIED, DATE-WRITTEN, INSTALLATION, REMARKS, SECURITY

Internal registers

| Register | Implemented | Definition |
|---------------------------|-------------|--------------------------------|
| 'ADDRESS OF' phrase | Yes | USAGE POINTER |
| COB-CRT-STATUS | Yes | PICTURE 9(4) USAGE DISPLAY |
| | | VALUE ZERO |
| DEBUG-ITEM | Yes | PICTURE X(n) USAGE DISPLAY |
| 'LENGTH OF' phrase | Yes | CONSTANT USAGE BINARY-LONG |
| NUMBER-OF-CALL-PARAMETERS | Yes | USAGE BINARY-LONG |
| RETURN-CODE | Yes | GLOBAL USAGE BINARY-LONG VALUE |
| | | ZERO |
| SORT-RETURN | Yes | GLOBAL USAGE BINARY-LONG VALUE |
| | | ZERO |
| TALLY | Yes | GLOBAL PICTURE 9(5) USAGE |
| | | BINARY VALUE ZERO |
| WHEN-COMPILED | Yes | CONSTANT PICTURE X(16) USAGE |
| | | DISPLAY |
| XML-CODE | Yes | GLOBAL PICTURE S9(9) USAGE |
| | | BINARY VALUE O |
| JSON-CODE | Yes | GLOBAL PICTURE S9(9) USAGE |
| | | BINARY VALUE O |

Appendix C2 - Intrinsic Functions

The following list of intrinsic functions was extracted from cobc --list-intrinsics and shows the names of the available functions, an implementation note and the number of parameters.

| Intrinsic Function | Implemented | Parameters |
|---------------------------|-------------|------------|
| ABS | Yes | 1 |
| ACOS | Yes | 1 |
| ANNUITY | Yes | 2 |
| ASIN | Yes | 1 |
| ATAN | Yes | 1 |
| BOOLEAN-OF-INTEGER | No | 2 |
| BYTE-LENGTH | Yes | 1 - 2 |
| CHAR | Yes | 1 |
| CHAR-NATIONAL | No | 1 |
| COMBINED-DATETIME | Yes | 2 |
| CONCAT | Yes | Unlimited |
| CONCATENATE | Yes | Unlimited |
| CONTENT-LENGTH | Yes | 1 |
| CONTENT-OF | Yes | 1 - 2 |
| COS | Yes | 1 |
| CURRENCY-SYMBOL | Yes | 0 |
| CURRENT-DATE | Yes | 0 |
| DATE-OF-INTEGER | Yes | 1 |
| DATE-TO-YYYYMMDD | Yes | 1 - 3 |
| DAY-OF-INTEGER | Yes | 1 |
| DAY-TO-YYYYDDD | Yes | 1 - 3 |
| DISPLAY-OF | No | 1 - 2 |
| E | Yes | 0 |
| EXCEPTION-FILE | Yes | 0 |
| EXCEPTION-FILE-N | No | 0 |
| EXCEPTION-LOCATION | Yes | 0 |
| EXCEPTION-LOCATION-N | No | 0 |
| EXCEPTION-STATEMENT | Yes | 0 |
| EXCEPTION-STATUS | Yes | 0 |
| EXP | Yes | 1 |
| EXP10 | Yes | 1 |
| FACTORIAL | Yes | 1 |
| FORMATTED-CURRENT-DATE | Yes | 1 |
| FORMATTED-DATE | Yes | 2 |
| FORMATTED-DATETIME | Yes | 4 - 5 |
| FORMATTED-TIME | Yes | 3 - 4 |
| FRACTION-PART | Yes | 1 |
| HIGHEST-ALGEBRAIC | Yes | 1 |
| INTEGER | Yes | 1 |
| INTEGER-OF-BOOLEAN | No | 1 |
| INTEGER-OF-DATE | Yes | 1 |
| INTEGER-OF-DAY | Yes | 1 |
| INTEGER-OF-FORMATTED-DATE | Yes | 2 |
| INTEGER-PART | Yes | 1 |
| LENGTH | Yes | 1 - 2 |

| LENGTH-AN | Yes | 1 |
|------------------------------|-----|-----------|
| LOCALE-COMPARE Yes 2 - 3 | | |
| LOCALE-DATE | Yes | 1 - 2 |
| LOCALE-TIME | Yes | 1 - 2 |
| LOCALE-TIME-FROM-SECONDS | Yes | 1 - 2 |
| LOG | Yes | 1 |
| LOG10 | Yes | 1 |
| LOWER-CASE | Yes | 1 |
| LOWEST-ALGEBRAIC | Yes | 1 |
| MAX | Yes | Unlimited |
| MEAN | Yes | Unlimited |
| MEDIAN | Yes | Unlimited |
| MIDRANGE | Yes | Unlimited |
| MIN | Yes | Unlimited |
| MOD | Yes | 2 |
| MODULE-CALLER-ID | Yes | 0 |
| MODULE-DATE | Yes | 0 |
| MODULE-FORMATTED-DATE | Yes | 0 |
| MODULE-ID | Yes | 0 |
| MODULE-PATH | Yes | 0 |
| MODULE-SOURCE | Yes | 0 |
| MODULE-TIME | Yes | 0 |
| MONETARY-DECIMAL-POINT | Yes | 0 |
| MONETARY-THOUSANDS-SEPARATOR | Yes | 0 |
| NATIONAL-OF | No | 1 - 2 |
| NUMERIC-DECIMAL-POINT | Yes | 0 |
| NUMERIC-THOUSANDS-SEPARATOR | Yes | 0 |
| NUMVAL | Yes | 1 |
| NUMVAL-C | Yes | 2 |
| NUMVAL-F | Yes | 1 |
| ORD | Yes | 1 |
| ORD-MAX | Yes | Unlimited |
| ORD-MIN | Yes | Unlimited |
| PI | Yes | 0 |
| PRESENT-VALUE | Yes | Unlimited |
| RANDOM | Yes | 0 - 1 |
| RANGE | Yes | Unlimited |
| REM | Yes | 2 |
| REVERSE | Yes | 1 |
| SECONDS-FROM-FORMATTED-TIME | Yes | 2 |
| SECONDS-PAST-MIDNIGHT | Yes | 0 |
| SIGN | Yes | 1 |
| SIN | Yes | 1 |
| SQRT | Yes | 1 |
| STANDARD-COMPARE | No | 2 - 4 |
| STANDARD-DEVIATION | Yes | Unlimited |
| STORED-CHAR-LENGTH | Yes | 1 |
| SUBSTITUTE | Yes | Unlimited |
| SUBSTITUTE-CASE | Yes | Unlimited |
| SUM | Yes | Unlimited |
| TAN | Yes | 1 |
| | | |

| TEST-DATE-YYYYMMDD | Yes | 1 |
|-------------------------|-----|-----------|
| TEST-DAY-YYYYDDD | Yes | 1 |
| TEST-FORMATTED-DATETIME | Yes | 2 |
| TEST-NUMVAL | Yes | 1 |
| TEST-NUMVAL-C | Yes | 2 |
| TEST-NUMVAL-F | Yes | 1 |
| TRIM | Yes | 1 - 2 |
| UPPER-CASE | Yes | 1 |
| VARIANCE | Yes | Unlimited |
| WHEN-COMPILED | Yes | 0 |
| YEAR-TO-YYYY | Yes | 1 - 3 |

Appendix C3 - System routines

The following list of system routines was extracted from cobc --list-system and shows the names of the available system routines along with the number of parameters.

| System routine | Parameters |
|----------------------|----------------|
| SYSTEM | 1 |
| CBL_AND | 3 |
| CBL_ALARM_SOUND | 0 |
| CBL_BELL_SOUND | 0 |
| CBL_CHANGE_DIR | 1 |
| CBL_CHECK_FILE_EXIST | 2 |
| CBL_CLOSE_FILE | 1 |
| CBL_COPY_FILE | 2 |
| CBL_CREATE_DIR | 1 |
| CBL_CREATE_FILE | 5 |
| CBL_DELETE_DIR | 1 |
| CBL_DELETE_FILE | 1 |
| CBL_EQ | 3 |
| CBL_ERROR_PROC | 2 |
| CBL_EXIT_PROC | 2 |
| CBL_FLUSH_FILE | 1 |
| CBL_GET_CSR_POS | 1 |
| CBL_GET_CURRENT_DIR | 3 |
| CBL_GET_SCR_SIZE | 2 |
| CBL_IMP | 3 |
| CBL_NIMP | 3 |
| CBL_NOR | 3 |
| CBL_NOT | 2 |
| CBL_OPEN_FILE | 5 |
| CBL_OR | 3 |
| CBL_READ_FILE | 5 |
| CBL_READ_KBD_CHAR | 1 |
| CBL_RENAME_FILE | 2 |
| CBL_SET_CSR_POS | 1 |
| CBL_TOLOWER | $\overline{2}$ |
| CBL_TOUPPER | 2 |
| CBL_WRITE_FILE | 5 |
| CBL_XOR | 3 |
| CBL_GC_FORK | 0 |
| CBL_GC_GETOPT | 6 |
| CBL_GC_HOSTED | 2 |
| CBL_GC_NANOSLEEP | 1 |
| CBL_GC_PRINTABLE | 1 - 2 |
| CBL_GC_WAITPID | 1 |
| CBL_OC_GETOPT | 6 |
| CBL_OC_HOSTED | 2 |
| CBL_OC_NANOSLEEP | 1 |
| C\$CALLEDBY | 1 |
| C\$CHDIR | 2 |
| | $\frac{2}{3}$ |
| C\$COPY | J |

| C\$DELETE | 2 |
|--------------|-------|
| C\$FILEINFO | 2 |
| C\$GETPID | 0 |
| C\$JUSTIFY | 1 - 2 |
| C\$MAKEDIR | 1 |
| C\$NARG | 1 |
| C\$PARAMSIZE | 1 |
| C\$PRINTABLE | 1 - 2 |
| C\$SLEEP | 1 |
| C\$TOLOWER | 2 |
| C\$TOUPPER | 2 |
| EXTFH | 2 |
| X"91" | 3 |
| X"E4" | 0 |
| X"E5" | 0 |
| X"F4" | 2 |
| X"F5" | 2 |

Appendix C4 - System names

The following list of system names was extracted from cobc --list-mnemonics and shows the system names categorized by their type.

System names: device

SYSIN, SYSIPT, STDIN, SYSOUT, SYSLIST, SYSLST, SYSPCH, SYSPUNCH, STDOUT, PRINTER, PRINTER-1, SYSERR, STDERR, CONSOLE

System names: feature

 $\texttt{C01}, \ \texttt{C02}, \ \texttt{C03}, \ \texttt{C04}, \ \texttt{C05}, \ \texttt{C06}, \ \texttt{C07}, \ \texttt{C08}, \ \texttt{C09}, \ \texttt{C10}, \ \texttt{C11}, \ \texttt{C12}, \ \texttt{S01}, \ \texttt{S02}, \ \texttt{S03}, \ \texttt{S04}, \ \texttt{S05}, \ \texttt{CSP}, \ \texttt{FORMFEED}, \ \texttt{TOP}, \ \texttt{CALL-CONVENTION}$

System names: switch

SWITCH-0, SWITCH-1, SWITCH-2, SWITCH-3, SWITCH-4, SWITCH-5, SWITCH-6, SWITCH-7, SWITCH-8, SWITCH-9, SWITCH-10, SWITCH-11, SWITCH-12, SWITCH-13, SWITCH-14, SWITCH-15, SWITCH-16, SWITCH-17, SWITCH-18, SWITCH-19, SWITCH-20, SWITCH-21, SWITCH-22, SWITCH-23, SWITCH-24, SWITCH-25, SWITCH-26, SWITCH-27, SWITCH-28, SWITCH-29, SWITCH-31, SWITCH-32, SWITCH-33, SWITCH-34, SWITCH-35, SWITCH-36

End of Appendix C — Grouped Reserved Word List

Appendix D - GNU Free Documentation License

Version 1.3, 3 November 2008

Copyright © 2000, 2001, 2002, 2007, 2008 Free Software Foundation, Inc. https://fsf.org/

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document free in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License.

A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

The "publisher" means any person or entity that distributes copies of the Document to the public.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.

- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work. In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements."

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, or distribute it is void, and will automatically terminate your rights under this License.

However, if you cease all violation of this License, then your license from a particular copyright holder is reinstated (a) provisionally, unless and until the copyright holder explicitly

and finally terminates your license, and (b) permanently, if the copyright holder fails to notify you of the violation by some reasonable means prior to 60 days after the cessation.

Moreover, your license from a particular copyright holder is reinstated permanently if the copyright holder notifies you of the violation by some reasonable means, this is the first time you have received notice of violation of this License (for any work) from that copyright holder, and you cure the violation prior to 30 days after your receipt of the notice.

Termination of your rights under this section does not terminate the licenses of parties who have received copies or rights from you under this License. If your rights have been terminated and not permanently reinstated, receipt of a copy of some or all of the same material does not give you any rights to use it.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See https://www.gnu.org/licenses/.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation. If the Document specifies that a proxy can decide which future versions of this License can be used, that proxy's public statement of acceptance of a version permanently authorizes you to choose that version for the Document.

11. RELICENSING

"Massive Multiauthor Collaboration Site" (or "MMC Site") means any World Wide Web server that publishes copyrightable works and also provides prominent facilities for anybody to edit those works. A public wiki that anybody can edit is an example of such a server. A "Massive Multiauthor Collaboration" (or "MMC") contained in the site means any set of copyrightable works thus published on the MMC site.

"CC-BY-SA" means the Creative Commons Attribution-Share Alike 3.0 license published by Creative Commons Corporation, a not-for-profit corporation with a principal place of business in San Francisco, California, as well as future copyleft versions of that license published by that same organization.

"Incorporate" means to publish or republish a Document, in whole or in part, as part of another Document.

An MMC is "eligible for relicensing" if it is licensed under this License, and if all works that were first published under this License somewhere other than this MMC, and subsequently incorporated in whole or in part into the MMC, (1) had no cover texts or invariant sections, and (2) were thus incorporated prior to November 1, 2008.

The operator of an MMC Site may republish an MMC contained in the site under CC-BY-SA on the same site at any time before August 1, 2009, provided the MMC is eligible for relicensing.

End of Appendix D — GNU Free Documentation License

Appendix E - Summary of Document Changes

GnuCOBOL is an ever-evolving tool. While all reasonable attempts will be made to maintain the currency of the information in this document, neither the author of this document nor the authors of the GnuCOBOL software extend any warranties of any kind for this document or for the information contained therein.

7th Edition

- 1. 2020. Changes from 2020.
- 2. 13/01 Added 'WITH SIZE' to screen ACCEPT and DISPLAY, missing since v2.0. Bug #612.
- 3. Added RETURNING | GIVING to GOBACK.
- 4. 14/04 Change version to 3.1 rc0 was 3.2 wrong!.
- 5. 09/05 Added text regarding compiler commands in 3.1 -D refers. Additional text regarding DISPLAY in 7.8.12.4 and 6.9.5.
- 6. 11/05 Added information regarding screen keys for supporting the mouse and some other missing values in 7.8.1.4. Thanks Eugenio (Di Lorenzo)
- 7. 16/05 Removed from 7.8.1.4 references to Mouse masks in the CRT status table.
- 8. 18/05 In 6.9.49 Packed Decimal should say In 'Picture Used' Yes not no.
- 9. 21/05 In 7.8.10 CONTINUE added the extension AFTER. (for v3.1 and later).
- 10. 24/05 In 8.9.49 Float Decimal 16 and 64 had wrong value for negatives.
- 11. 21/06 In 8.2.52 Added details for SYSTEM with return-code and GIVING clause.
- 12. 01/07 Updated version info to July 2020 for v3.1 RC1.
- 13. 02/07 Minor layout problem with SYN-ID-Overview chap 4.
- 14. 19/07 Clean up SELECT to reposition ORGANISATION (both spellings) and LOCK MODE. In 5.2.1 missing error conditions. CDF clean additions as of v3.1.
- 15. 31/07 By JKL adding html manual support via a makefile.
- 16. Pre-note on amendments changes Appendix D -> E.
- 17. 31/08 Minor grammar in sections 1 & 2 from comments by Aaric. Updates for 3.1 rc1 and 4.0+ Added missing numeric literals precedences B, BX, H, X, L, N, NX etc. Formatting changes and wholesale technical changes in use of appropriate texinfo commands.
- 18. 05/09 Minor grammar and layout for PD ACCEPT and DISPLAY statements.
- 19. 11/11 Full version release for v3.1 issued this day with manuals updated to reflect that.
- 20. 30/11 Added usage of UNBOUND as OCCURS format 4.
- 21. 4/12 The ALLOCATE verb was missing some information in formatting added.
- 22. 7/12 Extra rules added for usage of RETURNING in ALLOCATE.
- 23. 13/05/21 Clear out old changes.

8th Edition on release of v3.2 with some updates for 4.0+.

- 1. 2021.
 - 25/01 Updated version to v3.1.2 with date 25 Jan 21.
- 2. 29/01 Updated formats for OCCURS and now only using one file. Ditto for Quick Reference.
- 3. 7/02 Added procedure statement EXHIBIT, updated reserved words in Appendix C and removed same in Appendix B.
- 4. 4/03 Modified Exhibit points 1/2 to loose the blank lines.
- 5. 12/04 Updated text for CBL\_SET\_CSR\_POS, repos EXHIBIT to 15B.

- 6. 13/05 Updated USAGE for BINARY=C-LONG. Updated version to v3.2 with date 13 May 2021.
- 7. 15/05 Updated EXHIBIT and renumbered paragraphs.
- 8. 24/08 Added detail for ACCEPT DAY-OF-WEEK. Changed descriptive for Display screen-data-name removing screen and adding position specs see bug #743 now cleared.
- 9. 30/08 Change Appendix F to separate sections F1 through F4 adding changes for v3.1.1 and v4. Added updates.texi after E.texi for latest document updates.
- 10. 5/09 Added Intrinsic functions BIT-OF, BIT-TO-CHAR, HEX-OF, HEX-TO-CHAR as 8.1.105 thru 108.but needs resorting of # in 8.1. Updated definition for C\$SLEEP.
- 11. 12.09 Multi typo's in sections 2, 3.5, .14, 6.9.51, 8.1.64B (chgd 2 to V2, 12.2, spotted by Patrik Thank you for the updates.
- 12. 17/10 Extra information regarding LINE SEQUENTIAL file processing in 2.1.8 which refers to 10.2.3.4 and 10.2.3.7.
- 13. 17/10 CDF PAGE directive changes to details. Likewise to the Quick Reference manual.
- 14. 21/11 DIVIDE statement minor changes (#786).
- 15. 23/11 DIVIDE changed as 7.8.13.1 INTO and 13.3 BY, must have been asleep.
- 16. 25/11 Updated example listings in 10.1.1. updated to current default.conf in 10.1.5 as out of date.
- 17. 23/12 Update to START verb to make KEY compulsory for ISAM.
- 18. 24/12 Update to START added missing sub clauses [WITH SIZE] | [WITH LENGTH].
- 19. 25/12 Update to sections 10.2.2 and 10.2.3 to clarify where program modules are loaded from i.e., directories pointed to by COB\_LIBRARY-PATH and only if not found in PATH. Update to syntax diagran for START to clarify that SIZE and LENGTH keywords are mandatory words even if obvious. Updated description for COMBINED-DATETIME
- 20. 31/12 Update to section 6.8.1 change program names to Usage-Lengths and replace the source listing to be correct positioned on cc8 as well as giving o/p for 64bit Linux. Bug #799.

End of Appendix E — Summary of Document Changes

8th Edition on release of v3.2 with some updates for 4.0+.

- 1. 2021.
 - 25/01 Updated version to v3.1.2 with date 25 Jan 21.
- 2. 29/01 Updated formats for OCCURS and now only using one file. Ditto for Quick Reference.
- 3. 7/02 Added procedure statement EXHIBIT, updated reserved words in Appendix C and removed same in Appendix B.
- 4. 4/03 Modified Exhibit points 1/2 to loose the blank lines.
- 5. 12/04 Updated text for CBL\_SET\_CSR\_POS, repos EXHIBIT to 15B.
- 6. 13/05 Updated USAGE for BINARY=C-LONG. Updated version to v3.2 with date 13 May 2021.
- 7. 15/05 Updated EXHIBIT and renumbered paragraphs.
- 8. 24/08 Added detail for ACCEPT DAY-OF-WEEK. Changed descriptive for Display screen-data-name removing screen and adding position specs see bug #743 now cleared.

- 9. 30/08 Change Appendix F to separate sections F1 through F4 adding changes for v3.1.1 and v4. Added updates.texi after E.texi for latest document updates.
- 10. 5/09 Added Intrinsic functions BIT-OF, BIT-TO-CHAR, HEX-OF, HEX-TO-CHAR as 8.1.105 thru 108.but needs resorting of # in 8.1. Updated definition for C\$SLEEP.
- 11. 12.09 Multi typo's in sections 2, 3.5, .14, 6.9.51, 8.1.64B (chgd 2 to V2, 12.2, spotted by Patrik Thank you for the updates.
- 12. 17/10 Extra information regarding LINE SEQUENTIAL file processing in 2.1.8 which refers to 10.2.3.4 and 10.2.3.7.
- 13. 17/10 CDF PAGE directive changes to details. Likewise to the Quick Reference manual.
- 14. 21/11 DIVIDE statement minor changes (#786).
- 15. 23/11 DIVIDE changed as 7.8.13.1 INTO and 13.3 BY, must have been asleep.
- 16. 25/11 Updated example listings in 10.1.1. updated to current default.conf in 10.1.5 as out of date.
- 17. 23/12 Update to START verb to make KEY compulsory for ISAM.
- 18. 24/12 Update to START added missing sub clauses [WITH SIZE] | [WITH LENGTH].
- 19. 25/12 Update to sections 10.2.2 and 10.2.3 to clarify where program modules are loaded from i.e., directories pointed to by COB\_LIBRARY-PATH and only if not found in PATH. Update to syntax diagran for START to clarify that SIZE and LENGTH keywords are mandatory words even if obvious. Updated description for COMBINED-DATETIME
- 20. 31/12 Update to section 6.8.1 change program names to Usage-Lengths and replace the source listing to be correct positioned on cc8 as well as giving o/p for 64bit Linux. Bug #799.

Appendix F4 - Summary of Compiler Changes for COBOL Compiler v4 early dev

There may well be some changes made that are not documented here.

Taken from Grammar Changelog Febuary 2021.

1. General

- (Bison): dropped support for building with versions < 3.
- (C API): removed $cob\_set\_num\_params$.
- (cobc command-line options): added option -fno-fast-math to disable integer arithemtic optimisations.
- (cobc command-line options): removed -fif-cutoff.
- (cobc command-line options): added -G for experimental GDB use.
- (configure): fixed unwanted flags not being removed completely bug #627.
- (EXTFH): added support for the external file handler (EXTFH) interface, letting users provide a custom file handler.
- (EXTFH): the old OpenCOBOL EXTFH interface (built into GnuCOBOL with the -()-with-seqra-extfh and -()-with-index-extfh build options) has been marked as obsolete.
- (Jobs (-j compilation flag)): fixed bug #618.
- (libcob): internal library number increased from 4 to 5.
- (help2man documentation): fixed error when building.

2. Configuration options

- (Deleted compiler configuration options): select-working bug #421.
- (New compiler configuration options): align-opt, align-record, assign-variable, assign-using-variable, assign-ext-dyn, assign-disk-from, implicit-assign-dynamic-var, reference-bounds-check, same-as-clause and sync-left-right.
- (New runtime configuration options): \begin(itemize) \item bdb\\_byteorder (whether BDB should use native, big endian or little endian byte order). \item create\\_table (whether the ODBC\slash()OCI file handler should create a DDL file from an XFD file if no DDL exists). \item dups\\_ahead (whether a duplicates in an INDEXED file leads to file status 02). \item mf\\_ls\\_instab (whether to replace tabs by spaces which fill up to the next tab stop (tab stops set 8 spaces apart)). \item keycheck (check whether INDEXED file keys match the SELECT specification exactly). \end(itemize)
- (New runtime configuration environment variables): IO\\_OPTIONS, IX\\_OPTIONS, \linebreak LA\\_OPTIONS, LS\\_OPTIONS, RL\\_OPTIONS, SQ\\_OPTIONS and IO\\_\$x\$, where \$x\$ is any ASSIGN EXTERNAL name used in a program.

3. Compiler directives

• (\directiveindicator()SET directive): added XFD phrase.

4. Identification division

- (FUNCTION-ID clause): added recognition of PROTOTYPE phrase.
- (PROGRAM-ID clause): added recognition of PROTOTYPE and RESIDENT phrases.

5. Environment division

- (ALTERNATE RECORD KEY clause): allow literal in SUPPRESS WHEN clause.
- (ASSIGN clause): allow pipe syntax in literals.

6. Data division

• (SYNCHRONIZED clause): LEFT phrase is now marked as unimplemented bug #512.

7. Procedure division

- (COMMIT statement): added optional word TRANSACTION.
- (DELETE statement (file)): added ON EXCEPTION handlers.
- (File I-O): added support for multiple simultaneous file handlers.
- (File I-O): allow file-handler to be configured for individual files or organizations using environment variables (or dictionary files).
- (File I-O): added support for INDEXED files based on LMDB.
- (File I-O): added initial support for ODBC and OCI as file-handlers.
- (File I-O): changed file status for detecting bad data in line sequential files from 34 to 71.
- (File I-O): fixed issues with LINE SEQUENTIAL and OPEN I-O on platforms that require output to be flushed between read and write of a file.
- (INSPECT statement): fixed multiple TALLYING phrases being rejected bug #47
- (Procedure division header): fixed error when a variable-length parameter was not referenced bug #648.
- (Procedure division header): added recognition of z/OS-PARM-style main program parameter fr #357.
- (Reference modification): added out-of-bounds checks within IF statement conditions.
- (REWRITE statement): enabled for LINE SEQUENTIAL files.
- (ROLLBACK statement): added optional word TRANSACTION.
- (SET statement): added support for FH-()-FCD and FH-()-KEYDEF fr #349.
- (START statement (transaction)): added recognition of.
- (STRING statement): strengthened syntax checks bugs #653 and #488.
- (Tracing): fixed line numbers when tracing inside RECURSIVE programs bug #611.
- (UNSTRING statement): strengthened syntax checks (bugs #653 and #488.
- (WRITE statement (indexed)): fixed bug involving file status 21.

End of Appendix F4 Summary of Compiler Changes for v4 early dev

Appendix F3 - Summary of Compiler Changes for v3.1.1-Dev

NB: Some changes have been made to 3.1.1-dev which have not yet been merged up to 4.0-early-dev. They have been marked with an asterisk (\*).

There may well be some changes made that are not documented here.

Taken from Grammar Changelog Feb 2021.

General

- fixed NIST tests script for AIX support.
- (C API (configuration)): added cob\_set\_runtime\_option and cob\_get\_runtime\_option for specifying the file handle which printer output or trace output should go to.
- (C API (environment)): added function cob\_getenv\_direct.
- (C API (fields)): added functions cob\_get\_dbl\_param, cob\_get\_field\_constant, cob\_get\_field\_digits, cob\_get\_field\_scale, cob\_get\_field\_sign, cob\_get\_field\_size, cob\_get\_field\_str, cob\_get\_field\_str\_buffered, cob\_get\_field\_type, cob\_get\_param\_field, cob\_get\_param\_str, cob\_get\_param\_str\_bufffered, cob\_put\_dbl\_param, cob\_put\_field\_str, cob\_put\_field\_str, explain\_field\_type (feature requests frnoname(383) and frnoname(384)).
- (C API (version)): added libcob\_version and set\_libcob\_version for querying the version of libcob.
- (cobc command-line options): added -fcallfh (and COBOL-IT alias -use-extfh.
- (cobc command-line options): added -fdump to dump data of all modules on abend of program.
- (cobc command-line options): added -fno-dump to suppress dumps of data from certain sections.
- (cobc command-line options): disabled -fif-cutoff pending removal.
- (cobc command-line options): added -fno-remove-unreachable to disable removal of unreachable code.
- (cobc command-line options): -debug no longer implies -ftrace bug 449.
- (cobc command-line options): added -O0 for disabling optimisations fr 255.
- (cobc command-line options): replaced -tsymbols by -f(no-)tsysmbols.
- (cobc command-line options): added -fno-theader, -fno-tmessages and -fno-tsource to suppress parts of listings.
- (cobc command-line options): added -Wadditional to enable any messages not enabled by -Wall.
- (cobc command-line options): added -Wextra as alias for -W.
- (cobc command-line options): added -Wno-error.
- (cobc command-line options): added -Wno-dialect to suppress dialect-specific warnings.
- (cobc command-line options): added -Wother to enable miscellaneous warnings.
- (cobc command-line options): added -fgen-c-line-directives and -fgen-c-labels to enable generation of labels and directives indicating where generated C code came from in the original COBOL source.
- (cobc command-line options): honour POSIXLY\_CORRECT environment variable.
- (cobc command-line options): added -fec and -fno-ec to enable and disable exception checks.
- (cobc command-line options): added -f(no-)diagnostics-show-option, to show the command-line option resposible for a diagnostic message fr #386.

- (cobc command-line options): added -Wdangling-text to warn on source text beyond the program area (previously only part of -Wall).
- (cobc command-line options): -Wimplicit-define and -Wcorresponding are now enabled by default.
- (cobcrun): allow redirection of cobcrun's output bug #616.
- (cobcrun command-line options): renamed -runtime-conf to -runtime-config.
- (cobcrun command-line options): added -verbose.
- (cobcrun command-line options): expanded information in –info about the used curses library fr #385.
- (COBOL-85 NIST testsuite): tests can now be downloaded from Sourceforge when the NIST website is unavailable bug #563.
- (COBOL-85 NIST testsuite): tests can now be performed individually by running make in the test module directory.
- (Copyfiles): fixed segfault when GnuCOBOL tried and failed to open a copyfile bug #458.
- (Copyfiles): GnuCOBOL now checks for recursive copyfiles bug #467.
- (Debugging): Added debug logging for compiler developers (-()-enable-debug-log ./configure option).
- (Dependencies): GnuCOBOL now (optionally) depends on libxml2 (for XML I-O) and cJSON or JSON-C (for JSON I-O).
- (Dependencies): moved documentation of GnuCOBOL's requirements from README to new file DEPENDENCIES.
- (Dependencies): minimum Texinfo version increased to 6.1.
- (Documentation): added Markdown versions of README and DEPENDENCIES.
- (Documentation): updated SourceForge URL to new url (http://sourceforge.net/p/gnucobol/).
- (Documentation): fixed warnings and errors while generating texi documentation.
- (Documentation): improved portability of documentation generation scripts.
- (DJGGP support): added minimal support for DJGGP.
- (Error messages): runtime error messages now use translated versions (depending on a user's language).
- (Error messages): added checks for version control conflict markers in source code.
- (Error messages): increased default maximum number of error messages to 128 from 100.
- (Expressions): fixed bug #431, where decimal constants were not initialised in INITIAL programs.
- (Hardening): added ./configure option -()-enable-hardening to control hardening compilation options.
- (IBM i support): fixed segfault involving filepaths
- (Listings): fixed the substitution of tokens in quotes in copyfiles bug #494.
- (Listings): fixed some cases of cross-reference listings containing wrong line numbers.
- (Listings): now require the size of a listing page to be at least 20 lines.
- (Listings): fixed segfault in listing programs with large REPLACE arguments bug #515.
- (Listings): fixed stack overflow in listing programs long literals bug #569.

- (Mac OS support): some build issues fixed (see bugs #644 and #73).
- (Microsoft Visual C++): dropped support for Visual Studio 2005.
- (MinGW support): added script for generating binaries using MinGW.
- (MinGW support): fixed issue with output filenames containing a dash.
- (Modules): enabled running of modules generated with older versions of GnuCOBOL fr #239.
- (MPIR support): added as an alternative to GMP for GnuCOBOL's maths library.
- (Multiple programs): fixed crash when a single file contained a large number of programs and functions bug #666.
- (National literals): added Fujitsu NC national character literals fr #352.
- (National literals): fixed NX type literals being treated as alphanumeric bug #658.
- (Nested programs): fixed bug #435, where identifiers in the containing program where not propagated to the contained program, causing a segfault.
- (Nested programs): fixed bug #587, where a memory error occurred when a program was nested inside a program with the same name.
- (Numeric literals): added support for HP~COBOL octal literals (%ldots).
- (OrangeC support): added minimal support for OrangeC.
- (Recursion): fixed bug #222, where the return value was lost when returning from a recursive call.
- (Reserved words): allow users to make default reserved words aliases for other words.
- (Sandboxed builds): fixed bugs #73 and #576.
- (Screen section testsuite): added a manual testsuite for screen section functionality patch #26.
- (Signals): added error message for SIGFPE bug #434.
- (Solaris support): fixed errors and warnings when compiling in Solaris 10.
- (Tracing): added new options for controlling tracing (see fr(242)).
- (Translations): added Serbian and updated all others.
- (User-defined words): increased default maximum user-defined length to 63 characters (per COBOL~202X draft standard).
- (Windows support): renamed makedist.bat to makedist.cmd.
- (Windows support): fixed cison.dll not being included in distributions.
- (Windows support): makedist.cmd now uses VCPKG\_EXPORT\_DIR if set.

2. Configuration options

- (assign-clause compiler configuration option): added options external (equivalent to ibm) and dynamic (equivalent to mf).
- (assign-clause compiler configuration option): changed value to "external" (i.e. "ibm") in the BS2000, COBOL-85, COBOL-2002 and COBOL-2014 dialects.
- (IBM dialect): reserved words updated to Enterprise COBOL V6.2.
- (incorrect-conf-sec-order option): changed to "ok" from "error" in mf and default dialects.
- (MF dialect): added ARGUMENT-NUMBER and ARGUMENT-VALUE as reserved words.
- (New compiler configurations): realia for CA Realia II.

compiler configuration options): assign-disk-from, assign-ext-dyn, assign-variable, binary-comp-1, call-convention-mnemonic, assign-using-variable, call-convention-linkage, continue-after, display-special-fig-consts, dpc-in-data, free-redefines-position fr #211, hp-octal-literals, implicit-assign-dynamic-var, goto-entry, line-col-zero-default, local-implies-recursive\*, national-character-literals move-non-numeric-lit-to-numeric-is-zero, move-figurative-space-to-numeric, missing-statement, numeric-pointer, perform-without-varying-by, record-delimiter, record-delim-with-fixed-recs, records-mismatch-record-clause, ref-mod-zero-length\*, report-column-plus, screen-section-rules, sequential-delimiters, symbolic-constant, type-to-clause\*, usage-type\*, vsam-status, xml-generate-extra-phrases, zero-lengthliterals.

3. New runtime configuration options

- col\_just\_lrc (for enablingslash()disabling the LEFTslash()RIGHTslash()CENTER phrases of the report COLUMN clause),
- printer and display\_print\_pipe (for specifying what command should be executed before DISPLAY UPON PRINTER; similar to Micro Focus' COBPRINTER option);
- display\_print\_file (name of file which DISPLAY UPON PRINTER will append its output to), display\_punch\_file (name of file to created upon first DISPLAY UPON SYSPUNCH),
- mouse\_flags (to let mouse clicks move the cursor in ACCEPT),
- mouse\_interval (maximum time between mouse press and mouse release events for them to recognised as a click),
- trace\_format,
- dump\_file and
- dump\_width.
- Disabling a register also removes the reserved word with the same name, if it exists fr #278.
- Added COL and LIN.
- Use the system's file path separator instead of always using : (so the path separator is now; on Windows) bug #610).

4. Compiler directives

- (COPY statement): added support for copybook and library names containing periods as text-names. For example, "COPY copybook.cpy." is now accepted. See fr(344).
- (COPY statement): for "COPY copybook IN library", GnuCOBOL tries to resolve "library" using the environment variable "COB\_COPY\_LIB\_library", before testing as-is and, if that fails, ignoring library entirely.
- (COPY statement): copybook names containing an extensions are no longer searched for by adding further extensions to the name.
- (DISPLAY directives): allow a wider range of characters.
- (directive indicator() IF directive\*): improved syntax error handling.
- (textdollar()IF directive\*): added textdollar()END-IF as a scope terminator.
- (OPTIONS directive): added recognition of.
- (New Micro Focus directives): ADDRSV, ADDSYN, MAKESYN, OVERRIDE and REMOVE fr #210; ASSIGN, BOUND\*, CALLFH, CHECKNUM\*, COMP1, DPC-IN-DATA, and SSRANGE\*.
- (New Micro Focus directives\*): added detection of SPZERO.

- (directive indicator) REF-MOD-ZERO-LENGTH directive\*: added.
- (directive indicator) TURN directive\*: added experimental implementation.
- 5. Identification division
- 6. (OPTIONS paragraph): added support for ARITHMETIC clause.
- 7. Environment division
 - (ALTERNATE RECORD KEY clause): implemented split keys (SOURCE IS; fr #23 and sparse keys (SUPPRESS WHEN; fr #281.
 - (ALPHABET clause): added recognition of more pre-defined alphabets.
 - (ASSIGN clause): re-enabled use of linkage section or BASED items bug #421.
 - (ASSIGN clause): added SYSPCH and SYSPUNCH device-names for writing to a punch file (this is not related to CARD-PUNCH).
 - (ASSIGN clause): added device-names S01 through to S05.
 - (ASSIGN clause): allow "ASSIGN VARYING ldots".
 - (ASSIGN clause): strengthened syntax checks bug #553.
 - (ASSIGN clause): fixed bug #571 involving external-file-names.
 - (ASSIGN clause): added Micro Focus' DISK FROM phrase.
 - (CALL-CONVENTION phrase): added C and PASCAL fr #311.
 - (CLASS phrase): added recognition of ALPHANUMERICslash()NATIONAL and alphabet phrases.
 - (CLASS phrase): fixed bug #566, where class-names were not inherited by nested subprograms.
 - (CRT STATUS phrase): improved syntax checks.
 - (CURRENCY phrase): changed to emit error when CURRENCY SIGN other than "\$" is entered.
 - (CURRENCY phrase): improved error messages for invalid currency signs.
 - (CURSOR phrase): fixed bug #579, where the CURSOR data item was not used for the initially positioning the cursor in an ACCEPT statement.
 - (CURSOR phrase): fixed for data items of length 4 characters.
 - (EXTERN clause): improved error messages bug #446.
 - (FILE-CONTROL entries): added detection of the OSslash()VS-era phrases ACTUAL KEY, FILE-LIMIT, NOMINAL KEY, TRACK-AREA and TRACK-LIMIT.
 - (FILE STATUS clause): added detection of VSAM secondary status identifier fr #51.
 - (FILE STATUS clause): strengthened syntax checks bug #656.
 - (I-O-CONTROL paragraph): added detection of APPLY COMMIT clause (from the COBOL~202X draft standard).
 - (I-O-CONTROL paragraph): added detection of the OSslash()VS-era clauses CORE-INDEX, CYL-INDEX, CYL-OVERFLOW, EXTENDED-SEARCH, LOCK-HOLDING, MASTER-INDEX, PRINT-CONTROL, RECORD OVERFLOW, REORG-CRITERIA, WRITE-ONLY and WRITE-VERIFY.
 - \bullet (OBJECT-COMPUTER paragraph): added recognition of NATIONAL collating sequences.
 - (OCCURS clause): correctly implemented nested OCCURS DEPENDING tables (ODOSLIDE).
 - (PASSWORD clause): added detection of.

- (RECORD clause): fixed behaviour in the IBM dialect when the maximum record length does not match the length in the RECORD clause.
- (RECORD DELIMITER phrase): added support for BINARY-SEQUENTIAL and LINE-SEQUENTIAL phrases.
- (RECORD DELIMITER phrase): improved syntax checks bug #442.
- (RECORD KEY clause): implemented sparse keys fr #23.
- (RERUN clause): added detection of.
- (SELECT entry): fixed bug #619.
- (TOP phrase): added as mnemonic for ADVANCING PAGE.

8. Data division

- (88-level items): improved error messages when used in the wrong places.
- (ANY LENGTH clause): fixed bug #487, where literals moved to ANY LENGTH items were incorrectly truncated.
- (ANY LENGTH clause): fixed bug #511, where comparisons treated ANY LENGTH items as having just one character.
- (ANY LENGTH clause): fixed segfault when referencing linkage-section ANY LENGTH items in the first compiled program.
- (COLUMN clause): "COL +1" and similar clauses are no longer allowed; there must now be a space between the sign and the number.
- (COLUMN clause (screen)): added POS as synonym for COLUMN.
- (errno): can now access the C global variable errno by declaring a variable as EXTERNAL AS "errno" fr #49.
- (LIKE clause\*): added recognition of (see fr(193)).
- (LINE clause): "LINE +1" and similar clauses are no longer allowed; there must now be a space between the sign and the number.
- (LINE clause (report)): allow LINES instead of LINE.
- (Local-storage section\*): in the Micro~Focus dialect, the presence of a local-storage section now implicitly defines a program as RECUR SIVE.
- (OCCURS clause): fixed issues with OCCURS UNBOUNDED.
- (PICTURE clause): added recognition of PIC 1(n).
- (PICTURE clause): improved error messages.
- (PICTURE clause): added recognition of LOCALE phrase.
- (PICTURE clause\*): fixed compiler crash with malformed picture-string bug #659.
- \bullet (RECORD VARYING clause): added warning under -Wadditional for an FD with RECORD VARYING but with records of only one size bug #441.
- (RENAMES clause): strengthened syntax checks.
- (RENAMES clause): fixed bug #623, where RENAMES items had a LENGTH OF zero.
- (SAME AS clause): implemented fr #193.
- (Screen section): made some COBOL words context-sensitive to screen section.
- (Screen description): the rules on which clauses must be specified when now depend on the dialect bug #382.
- (SYNCHRONIZED clause): deactivated RIGHT phrase, pending correct implementation (previously SYNCHRONIZED RIGHT was the same as SYNCHRONIZED LEFT).

- (TYPE clause\*): added type-name format.
- (TYPEDEF clause\*): implemented fr #193.
- (USAGE clause): added option to make COMP-1 mean a 16-bit signed integer fr #272.
- (USAGE clause): added recognition of BIT and COMP-0.
- (USAGE clause): added COMP-N.
- (USAGE clause): added experimental support for ACUCOBOL's numeric POINTER fr #376.
- (USAGE clause\*): added type-names.
- (VOLATILE clause): added recognition of.

9. Procedure division

- (ACCEPT statement (environment)): added recognition of INPUT~STATUS and TERMINAL-INFO and SYSTEM-INFO phrases.
- (ACCEPT statement (screen)): fixed ACCEPT WITH UPDATE and not working bug #423.
- (ACCEPT statement (screen)): fixed bug #426, where backspacing at the start of a field moved the cursor to the second-to-last character of the preceding field.
- (ACCEPT statement (screen)): added detection of CONTROL KEY clause.
- (ACCEPT statement (screen)): allow numeric-edited fields to contain spaces bug #491.
- (ACCEPT statement (screen)): fixed error when filling in a one character field with insert mode on bug #498.
- (ACCEPT statement (screen)): pressing the home key, or end key, now toggles between going to the start of, or end of, the field and the cursor's original position.
- (ACCEPT statement (screen)): added WITH NO BELL clause.
- (ACCEPT statement (screen)): added support for Microsoft COBOL position specifiers.
- (ACCEPT statement (screen)): removed silent minimum of 500~ms from TIME-OUT phrase fr #196.
- (ACCEPT statement (screen)): added recognition of CURSOR clause.
- (ACCEPT statement (screen)): fixed some issues with mice.
- (ACCEPT statement (screen)): improved numeric entry
 - prevent deletion, backspacing over or overwriting of decimal point;
 - entering a decimal point now jumps to character after it;
 - allow entry of plusslash()minus signs;
 - added new insert behaviour: cursor on integral digits inserts to right, cursor on decimal digits inserts to left, cursor starts on rightmost integer digit upon entering field, GnuCOBOL beeps at last character only when no insertion is possible.
- (ACCEPT statement (temporal)): fixed bug #469, where ACCEPT FROM DAY was off by \$-1\$.
- (ALLOCATE statement): added recognition of LOC clause.
- (CALL statement): fixed ON EXCEPTION not working properly with -fstatic bug #462.
- (CALL statement): added LINKAGE phrase fr #311.
- (CALL statement\*): fixed RETURN-CODE being set with RETURNING field bug #651.

- (CANCEL statement): fixed segfault in recursive programs bug #98.
- (Conditions): strengthened syntax checks for abbreviated conditions.
- (Conditions): improved error messages bug #567.
- (Conditions): fixed LESS OR EQUAL being accepted, but LESS OR EQUALS being rejected bug #663.
- (CONTINUE (after)): added support for (from COBOL~202X draft standard). See fr #354.
- (DISPLAY statement (printer)): allow for redirecting DISPLAY UPON PRINTER(-1) to files based on the runtime configuration.
- (DISPLAY statement (screen)): fixed DISPLAY LOW-VALUE not setting position of cursor for next DISPLAY statement bug #423.
- (DISPLAY statement (screen)): added configuration option to disable Micro Focus' special behaviour with some figurative constants bug #423.
- (DISPLAY statement (screen)): fixed bug #428, where DISPLAY ALL "x" WITH SIZE only displayed "x" once.
- (DISPLAY statement (screen)): added support for Microsoft COBOL's position specifiers and ERASE phrase.
- (DISPLAY statement (screen)\*): fixed bug #665, where spaces where replaced with underscores in "DISPLAY ldots USING".
- (ENTRY statement): added LINKAGE phrase fr #311.
- (Error messages): runtime error messages now include "error:" after the filename and before the actual error message.
- (Error messages): fixed incorrect use of "parameter" where "argument" was meant.
- (Error messages): fixed bug #586, where GnuCOBOL would cause a buffer overflow when outputting an error message with a very long literal.
- (EVALUATE statement): added partial support for WHEN clauses not containing any statements, which transfer control to the next WHEN clause containing a statement, if any (so the behaviour is like C's switch statement).
- (Exceptions): the exception status is now only reset by SET LAST EXCEPTION TO OFF.
- (Exceptions): fixed EC-SIZE-OVERFLOW being raised when EC-SIZE-ZERO-DIVIDE is active bug #223.
- (EXHIBIT statement): added.
- (File I-O): fixed bug #457, where file status 30 was set instead of the correct permanent error status (34, 35 or 37).
- (File I-O): added support for VBISAM 2.1.1.
- (File I-O): error messages from libcob now include the file I-O statement that caused them, when known.
- (File I-O): added support for file locking on Windows.
- (File I-O): filenames starting with a period or a number are no longer resolved; periods in an external-file-name are always replaced by an underscore (so "MY.FILE" will be resolved as "DD\_MY\_FILE", "dd\_MY\_FILE" or "MYFILE").
- (File I-O): filename mapping is now applied in called subroutines.
- (File I-O (BDB)): fixed file status after OPEN OUTPUT on an OPTIONAL file.
- (File I-O (ISAM)): fixed bug involving START ldots LESS EQUAL followed by READ PREVIOUS.

- (File I-O (ISAM)): fixed bug #589, where READ would skip records with duplicate keys after a DELETE.
- (Floating-point arithmetic): fixed incorrect SIZE ERROR exceptions bug #470.
- (Floating-point arithmetic): fixed bug #478, where calculations with the SIZE ERROR phrase have different results to calculations without it.
- (Floating-point arithmetic): now activate the SIZE ERROR handler when a floating-point variable is set to a non-finite value bug #122.
- (GO TO statement): added non-standard ENTRY phrase extension.
- (INITIALIZE statement): optimised.
- (INQUIRE statement): added recognition of.
- (INSPECT statement): optimised.
- (JSON GENERATE statement): added patch #45.
- (JSON PARSE statement): added recognition of.
- (LENGTH OF phrase): fixed error message when used on group fields bug #175.
- (LENGTH OF phrase): allow non-numeric literals.
- (MODIFY statement): added recognition of.
- (MOVE statement): added options to interpret moving non-numeric values to numeric items as moving zero to numeric items.
- (MOVE statement): improved detection of overlapping MOVEs when using reference modification.
- (MOVE statement): fixed remaining cases of bug #220, involving numeric-edited items.
- (MOVE statement): fixed incorrect truncation of COMP-4 items.
- (PERFORM statement): added check for non-zero item in BY phrase fr #268.
- (PERFORM statement): allow the BY phrase to be omitted, which is the same as specifying BY 1 fr #158.
- (PERFORM statement (inline)): added partial support for inline PERFORM statements not containing any statements.
- (Procedure division header): added recognition of MEMORY SIZE phrase.
- (Procedure division header): added LINKAGE phrase fr #311.
- (Procedure division header): error if two USING BY REFERENCE parameters are the same bug #635.
- (Procedure division header\*): fixed use of variable-length RETURNING item bug #641.
- (Procedure division header\*): disabled RETURNING in programs, pending fix of bug #650).
- (RAISE statement): added recognition of.
- (READ statement (relative)): fixed file status on end of file.
- (Reference modification): improved out-of-bounds error message bug #445.
- (Reference modification\*): allow zero-length reference modification fr #390.
- (SORT statement): added sorting of tables without keys patch #42.
- (SORT statement): added recognition of more COLLATING SEQUENCE phrases.
- (OPEN statement): fail with file status 39 when the first record of an indexed file is larger than specified in the FD.

- (OPEN statement): fixed segfault when attempting to open a file in a non-existent folder bug #520.
- (OPEN statement): added ACUCOBOL locking clauses.
- (OPEN statement): added detection of OSslash()VS-era input mode phrases.
- (READ statement (indexed)): fail with file status 43 when the read record is larger than specified in the FD.
- (Reference modification): added warnings for invalid reference modifications involving variables.
- (Report writer): implemented, including features from COBOL 2002 and the IBM Report Writer.
- (REWRITE statement (indexed)): now sets file status to 02 when duplicate key is detected.
- (SET statement): fixed bug #225, where an invalid SET statement caused an error saying "invalid MOVE statement".
- (STRING statement): fixed bug #543.
- (STRING statement): strengthened syntax checks bug #653.
- (SUBTRACT statement): fixed bug #603, where subtracting an integer from a floating-point variable lead to incorrect results.
- (STOP statement): fixed the NORMAL phrase causing a compilation error bug #433.
- (UNSTRING statement): strengthened syntax checks bug #653.
- (USE statement (exception)): improved recognition of.
- (VALIDATE statement): added recognition of.
- (WRITE statement): fixed compilation error when writing to a GLOBAL file in a subprogram bug #87.
- (WRITE statement (indexed)): now sets file status to 02 when duplicate key is detected.
- (XML GENERATE statement): added patch #41.
- (XML PARSE statement): added recognition of.

10. Intrinsic functions

- (CONCAT function): added.
- (CONTENT-OF function): added.
- (CONTENT-LENGTH function): added.
- (LENGTH, BYTE-LENGTH and LENGTH-AN functions): now forbid numeric arguments.
- (MOD function): fixed EC-SIZE-ZERO-DIVIDE being raised instead of EC-ARGUMENT-FUNCTION when zero was provided as an argument.
- (REM function): fixed EC-SIZE-ZERO-DIVIDE being raised instead of EC-ARGUMENT-FUNCTION when zero was provided as an argument.
- \bullet (WHEN-COMPILED function): fixed timezone, which was missing its sign and contained nonsense when negative bug #436.

11. Built-in subprograms

- (C\$GETPID): fixed wrong process ID being returned after forking bug #451.
- (C\$SLEEP): if the requested time is too large, sleep for the maximum possible time instead of not at all.

- (CBL\_GET\_CSR\_POS): fixed wrong position being returned after ACCEPT statement bug #483.
- (CBL\_READ\_KBD\_CHAR): this now works bug #500.
- (SYSTEM): added workaround of buggy system() implementation on Windows, which removes leading and trailing quotes.
- (X"91"): corrected number of arguments from 2 to 3 bug #527.

| End | of Apper | dix F3 | Summar | y of C | $^{ m compiler}$ | Changes | for v | v3.1.1- | Dev |
|-----|----------|--------|--------|--------|------------------|---------|-------|---------|-----|

Appendix F2 - Summary of Compiler Changes after GnuCOBOL Compiler v2.2

There may well be some changes made that are not documented here.

Taken from Grammar Changelog June 2019.

1. General

- C API (configuration): added cob\_set\_runtime\_option and cob\_get\_runtime\_option for specifying the file handle which printer output or trace output should go to.
- cobc command-line options: added -fcallfh (and COBOL-IT alias -use-extfh).
- cobc command-line options: added -fdump to dump data of all modules on abend of program.
- cobc command-line options: disabled -fif-cutoff pending removal.
- cobc command-line options: added -fno-remove-unreachable to disable removal of unreachable code.
- cobc command-line options: -debug no longer implies -ftrace (bug #449).
- cobc command-line options: added -O0 for disabling optimisations (feature request #255).
- cobc command-line options: replaced -tsymbols by -f(no)-tsysmbols.
- cobc command-line options: added -fno-theader, -fno-tmessages and -fno-tsource to suppress parts of listings.
- cobc command-line options: added -Wno-dialect to suppress dialect-specific warnings.
- cobc command-line options: added -Wother to enable miscellaneous warnings.
- cobcrun command-line options: renamed -runtime-conf to -runtime-config.
- COBOL-85 NIST testsuite: tests can now be downloaded from Sourceforge when the NIST website is unavailable (bug #563).
- COBOL-85 NIST testsuite: tests can now be performed individually by running make in the test module directory.
- Copyfiles: fixed segfault when GnuCOBOL tried and failed to open a copyfile (bug #458).
- Copyfiles: GnuCOBOL now checks for recursive copyfiles (bug #467).
- Debugging: Added debug logging for compiler developers (-enable-debug-log).
- Dependencies: GnuCOBOL now (optionally) depends on libxml2 and cJSON (for XML and JSON I-O).
- DJGGP support: added minimal support for DJGGP.
- Error messages: runtime error messages now use translated versions (depending on a user's language).
- Error messages: added checks for version control conflict markers in source code.
- Expressions: fixed bug #431, where decimal constants were not initialised in INITIAL programs.
- EXTFH: added support for the external file handler (EXTFH) interface, letting users provide a custom file handler.
- IBM i support: fixed segfault involving filepaths
- Listings: fixed the substitution of tokens in quotes in copyfiles (bug #494).
- Listings: fixed some cases of cross-reference listings containing wrong line numbers.
- Listings: now require the size of a listing page to be at least 20 lines.

- Listings: fixed segfault in listing programs with large REPLACE arguments (bug #515).
- Modules: enabled running of modules generated with older versions of GnuCOBOL (feature request #239).
- National literals: added Fujitsu NC national character literals (feature request #352).
- Nested programs: fixed bug #435, where identifiers in the containing program where not propagated to the contained program, causing a segfault.
- OrangeC support: added minimal support for OrangeC.
- Recursion: fixed bug #222, where the return value was lost when returning from a recursive call.
- Reserved words: allow users to make default reserved words aliases for other words.
- Screen section testsuite: added a manual testsuite for screen section functionality patch #26.
- Signals: added error message for SIGFPE (bug #434).
- Solaris support: fixed errors and warnings when compiling in Solaris 10.
- Tracing: added new options for controlling tracing (feature request #242).
- User-defined words: increased default maximum user-defined length to 63 characters (per COBOL~202X draft standard).

2. Configuration options

- IBM dialect: reserved words updated to Enterprise COBOL V6.2.
- incorrect-conf-sec-order option: changed to "ok" from "error" in mf and default dialects.
- New compiler configuration options: binary-comp-1, call-convention-mnemonic, call-convention-linkage, continue-after, display-special-fig-consts, free-redefines-position (feature request #211), line-col-zero-default, national-character-literals move-figurative-space-to-numeric, move-non-numeric-lit-to-numeric-is-zero, missing-statement, perform-without-varying-by, record-delimiter, record-delim-with-fixed-recs, records-mismatch-record-clause, screen-section-rules, sequential-delimiters, symbolic-constant, xml-generate-extra-phrases, zero-length-literals.
- New runtime configuration options: col\_just\_lrc (for enabling disabling the LEFT slash RIGHT slash CENTER phrases of the report COLUMN clause), printer and display\_print\_pipe (for specifying what command should be executed before DISPLAY UPON PRINTER; similar to Micro Focus' COBPRINTER option); display\_print\_file (name of file which DISPLAY UPON PRINTER will append its output to), display\_punch\_file (name of file to created upon first DISPLAY UPON SYSPUNCH), trace\_format, dump\_file and dump\_width.
- Registers: disabling a register also removes the reserved word with the same name, if it exists (feature request #278).
- Registers: added COL and LIN. added LINKAGE phrase.

3. Compiler directives

- COPY statement: added support for copybook and library names containing periods as text-names. For example, "COPY copybook.cpy." is now accepted. See feature request #344.
- Fujitsu OPTIONS directive: added recognition of.
- New directives: ADDRSV, ADDSYN, MAKESYN, OVERRIDE and REMOVE (feature request #210); CALLFH and COMP1.

4. Identification division

• OPTIONS paragraph: added support for ARITHMETIC clause.

5. Environment division

- ALTERNATE RECORD KEY clause: implemented split keys (SOURCE IS; feature request #23) and sparse keys (SUPPRESS WHEN; feature request #281).
- ALPHABET clause: added recognition of more pre-defined alphabets.
- ASSIGN clause: re-enabled use of linkage section or BASED items (bug #421).
- ASSIGN clause: added SYSPCH and SYSPUNCH device-names for writing to a punch file (this is not related to CARD-PUNCH).
- ASSIGN clause: added device-names S01 through to S05.
- CALL-CONVENTION phrase: added C and PASCAL (see feature request #311).
- CLASS phrase: added recognition of ALPHANUMERIC NATIONAL and alphabet phrases.
- CLASS phrase: fixed bug #566, where class-names were not inherited by nested subprograms.
- CURRENCY phrase: changed to emit error when CURRENCY SIGN other than '\$' is entered.
- CURRENCY phrase: improved error messages for invalid currency signs.
- EXTERN clause: improved error messages (bug #446).
- FILE STATUS clause: added detection of VSAM secondary status identifier (feature request #51).
- I-O-CONTROL paragraph: added detection of APPLY COMMIT clause (from the COBOL~202X draft standard).
- OBJECT-COMPUTER paragraph: added recognition of NATIONAL collating sequences.
- OCCURS clause: correctly implemented nested OCCURS DEPENDING tables (ODOSLIDE).
- PASSWORD clause: added detection of.
- RECORD clause: fixed behaviour in the IBM dialect when the maximum record length does not match the length in the RECORD clause.
- RECORD DELIMITER phrase: added support for BINARY-SEQUENTIAL and LINE-SEQUENTIAL phrases.
- RECORD DELIMITER phrase: improved syntax checks (see bug #442).
- RECORD KEY clause: implemented sparse keys (SOURCE IS; feature request #23).

6. Data division

- 88-level items: improved error messages when used in the wrong places.
- ANY LENGTH clause: fixed bug #487, where literals moved to ANY LENGTH items were incorrectly truncated.
- ANY LENGTH clause: fixed bug #511, where comparisons treated ANY LENGTH items as having just one character.
- ANY LENGTH clause: fixed segfault when referencing linkage-section ANY LENGTH items in the first compiled program.
- COLUMN clause: "COL +1" and similar clauses are no longer allowed; there must now be a space between the sign and the number.
- COLUMN clause (screen): added POS as synonym for COLUMN.

- LINE clause: "LINE +1" and similar clauses are no longer allowed; there must now be a space between the sign and the number.
- LINE clause (report): allow LINES instead of LINE.
- PICTURE clause: added recognition of PIC 1(n).
- PICTURE clause: improved error messages.
- PICTURE clause: added recognition of LOCALE phrase.
- RECORD VARYING clause: fixed bug #441, where an FD could be declared as RECORD VARYING, but have records of only one size.
- Screen section: made some COBOL words context-sensitive to screen section.
- Screen description: the rules on which clauses must be specified when now depend on the dialect (see bug #382).
- SYNCHRONIZED clause: deactivated RIGHT phrase, pending correct implementation (previously SYNCHRONIZED RIGHT was the same as SYNCHRONIZED LEFT).
- \bullet USAGE clause: added option to make COMP-1 mean a 16-bit signed integer (feature request #272).
- USAGE clause: added recognition of BIT and COMP-0.
- USAGE clause: added COMP-N.
- VOLATILE clause: added recognition of.

7. Procedure division

- ACCEPT statement (environment): added recognition of INPUT~STATUS and TERMINAL-INFO and SYSTEM-INFO phrases.
- ACCEPT statement (screen): fixed ACCEPT WITH UPDATE and not working (bug #423).
- ACCEPT statement (screen): fixed bug #426, where backspacing at the start of a field moved the cursor to the second-to-last character of the preceding field.
- ACCEPT statement (screen): added detection of CONTROL KEY clause.
- ACCEPT statement (screen): allow numeric-edited fields to contain spaces (see bug #491).
- ACCEPT statement (screen): fixed error when filling in a one character field with insert mode on (bug #498).
- ACCEPT statement (screen): pressing the home key, or end key, now toggles between going to the start of, or end of, the field and the cursor's original position.
- ACCEPT statement (screen): added WITH NO BELL clause.
- ACCEPT statement (screen): added support for Microsoft COBOL position specifiers.
- ACCEPT statement (temporal): fixed bug #469, where ACCEPT FROM DAY was off by \$-1\$.
- ALLOCATE statement: added recognition of LOC clause.
- CALL statement: fixed ON EXCEPTION not working properly with -fstatic (bug #462).
- CALL statement: added LINKAGE phrase (feature request #311).
- CANCEL statement: fixed segfault in recursive programs (bug #98).
- Conditions: strengthened syntax checks for abbreviated conditions.
- Conditions: improved error messages (bug #567).
- CONTINUE (after): added support for (from COBOL~202X draft standard). See feature request #354.

- DISPLAY statement (printer): allow for redirecting DISPLAY UPON PRINTER(-1) to files based on the runtime configuration.
- DISPLAY statement (screen): fixed DISPLAY LOW-VALUE not setting position of cursor for next DISPLAY statement (bug #423).
- DISPLAY statement (screen): added configuration option to disable Micro Focus' special behaviour with some figurative constants (see bug #423).
- DISPLAY statement (screen): fixed bug #428, where DISPLAY ALL "x" WITH SIZE only displayed "x" once.
- DISPLAY statement (screen): added support for Microsoft COBOL's position specifiers and ERASE phrase.
- ENTRY statement: added LINKAGE phrase (feature request #311).
- Error messages: runtime error messages now include "error:" after the file before the actual error message.
- EVALUATE statement: added partial support for WHEN clauses not containing any statements, which transfer control to the next WHEN clause containing a statement, if any (so the behaviour is like C's switch statement).
- Exceptions: the exception status is now only reset by SET LAST EXCEPTION TO OFF.
- Exceptions: fixed EC-SIZE-OVERFLOW being raised when EC-SIZE-ZERO-DIVIDE is active (bug #223).
- File I-O: fixed bug #457, where file status 30 was set instead of the correct permanent error status (34, 35 or 37).
- File I-O: added support for VBISAM 2.1.1.
- File I-O: error messages from libcob now include the file I-O statement that caused them, when known.
- Floating-point arithmetic: fixed incorrect SIZE ERROR exceptions (see bug #470).
- Floating-point arithmetic: fixed bug #478, where calculations with the SIZE ERROR phrase have different results to calculations without it.
- Floating-point arithmetic: now activate the SIZE ERROR handler when a floating-point variable is set to a non-finite value (see bug #122).
- INQUIRE statement: added recognition of.
- JSON GENERATE statement: added patch #45).
- JSON PARSE statement: added recognition of.
- LENGTH OF phrase: fixed error message when used on group fields (bug #175).
- LENGTH OF phrase: allow non-numeric literals.
- MODIFY statement: added recognition of.
- MOVE statement: added options to interpret moving non-numeric values to numeric items as moving zero to numeric items.
- MOVE statement: improved detection of overlapping MOVEs when using reference modification.
- MOVE statement: fixed remaining cases of bug #220, involving numeric-edited items.
- MOVE statement: fixed incorrect truncation of COMP-4 items.
- PERFORM statement: added check for non-zero item in BY phrase (feature request #268).
- PERFORM statement: allow the BY phrase to be omitted, which is the same as specifying BY 1 (feature request #158).

- PERFORM statement (inline): added partial support for inline PERFORM statements not containing any statements.
- Procedure division header: added recognition of MEMORY SIZE phrase.
- Procedure division header: added LINKAGE phrase (feature request #311).
- RAISE statement: added recognition of.
- Reference modification: improved out-of-bounds error message (bug #445).
- SORT statement: added sorting of tables without keys patch #42).
- SORT statement: added recognition of more COLLATING SEQUENCE phrases.
- OPEN statement: fail with file status 39 when the first record of an indexed file is larger than specified in the FD.
- OPEN statement: fixed segfault when attempting to open a file in a non-existent folder (bug #520).
- OPEN statement: added ACUCOBOL locking clauses.
- READ statement (indexed): fail with file status 43 when the read record is larger than specified in the FD.
- Reference modification: added warnings for invalid reference modifications involving variables.
- Report writer: implemented, including features from COBOL 2002 and the IBM Report Writer.
- REWRITE statement (indexed): now sets file status to 02 when duplicate key is detected.
- SET statement: fixed bug #225, where an invalid SET statement caused an error saying "invalid MOVE statement".
- STOP statement: fixed the NORMAL phrase causing a compilation error (bug #433).
- USE statement (exception): improved recognition of.
- VALIDATE statement: added recognition of.
- WRITE statement: fixed compilation error when writing to a GLOBAL file in a subprogram (bug #87).
- WRITE statement (indexed): now sets file status to 02 when duplicate key is detected.
- XML GENERATE statement: added patch #41.
- XML PARSE statement: added recognition of.

8. Intrinsic functions

- CONTENT-OF function: added.
- CONTENT-LENGTH function: added.
- LENGTH, BYTE-LENGTH and LENGTH-AN functions: now forbid numeric arguments.
- MOD function: fixed EC-SIZE-ZERO-DIVIDE being raised instead of EC-ARGUMENT-FUNCTION when zero was provided as an argument.
- REM function: fixed EC-SIZE-ZERO-DIVIDE being raised instead of EC-ARGUMENT-FUNCTION when zero was provided as an argument.
- X"91" function: corrected number of arguments from 2 to 3 (bug #527).
- WHEN-COMPILED function: fixed timezone, which was missing its sign and contained nonsense when negative (bug #436).

9. Built-in subprograms

• \$GETPID: fixed wrong process ID being returned after forking (bug #451).

- \$SLEEP: if the requested time is too large, sleep for the maximum possible time instead of not at all.
- CBL\_READ\_KBD\_CHAR: this now works (bug #500).
- SYSTEM: added workaround of buggy system() implementation on Windows, which removes leading and trailing quotes.

End of Appendix F2 Summary of Compiler Changes since 2009 and version v2.2

Appendix F1 - Summary of Compiler Changes since 2009 and version v1-1

To GnuCOBOL Compiler v2.2.

Taken from Grammar Changelog Sept 2017.

1. General

- $\bullet\,$ 64-bit numbers: fixed bugs in handling of 64-bit numbers bug #229.
- ACUCOBOL windows: added detection of ACUCOBOL's window/message box GUI syntax.
- C API (data): added several functions for getting and setting cob\_field items.
- C API (files): added cob\_file\_external\_addr, cob\_file\_malloc and cob\_file\_free.
- C API (screen): added several functions from Micro Focus C to COBOL API: cob\_display\_text, cob\_sys\_get\_char, cob\_get\_char, cob\_get\_text, cob\_display\_formatted\_text, cob\_sys\_get\_csr\_pos, cob\_sys\_set\_csr\_pos, cob\_move, cobaddstrc, cobprintf and cobgetch (feature requests #148 and #187).
- C API (signals): added cob\_raise to send signal to signal handlers.
- C compiler support: fixed errors in compilers without designated initializers.
- cobc command-line options: added -O3 to enable more optimisations.
- cobc command-line options: added -Wfatal-error to make the compiler abort on the first error.
- cobc command-line options: added -Wpossible-overlap to warn items that may overlap (-Woverlap only warns if items definitely overlap).
- cobc command-line options: added -fmax-errors to set number of errors at which the compiler aborts.
- cobc command-line options: added -fwinmain to output WinMain instead of main (feature request #194).
- cobc command-line options: added -t and -T for complete listing support (-t for 80-characters wide listings and -T for 132-characters wide) which includes crossreferences.
- cobc command-line options: added -vvv (like -vv but passes verbose option to the linker as well) and -### (like -v but commands are not executed).
- cobc command-line options: allow -, i.e. stdin, as a source file.
- COBOL-85 NIST testsuite: tests now refer to \$COBC, \$COBCRUN and \$COBCRUN\_DIRECT environment variables instead of directly calling cobc and cobcrun, allowing the testsuite to run in conjunction with tools like valgrind.
- COBOL-85 NIST testsuite: tests for obsolete feature flagging are now executed, if possible.
- Comments: added ACUCOBOL comments: \$ as synonym for \* in indicator area and j as synonym for floating comment indicator \*>.
- Communication facility: added detection of communication facility syntax.
- configure: added useful error message when help2man, bison and flex are missing when they are needed.
- curses: fixed compilation errors when configured without curses (bug #90).
- Error messages: error messages are now lowercase, in line with the GNU Coding Standards (bug #198).
- Error messages: segfaults in the compiler now cause an error message to be displayed.
- Error messages: replaced instances of "ODO" by the clearer "OCCURS DEPENDING ON".

- Expressions: resolve constant expressions and optimise constant decimals at compile time.
- Expressions: added support for IBM OS/VS COBOL's arithmetic.
- Expressions: improved error messages for malformed expressions.
- Indicators: invalid indicators no longer cause compilation to immediately terminate (feature request #126).
- Information: output compiler version used to build GnuCOBOL and any mathematical libraries used (feature request #169).
- Information: output what a reserved word is an alias for in the -list-reserved output (feature request #214).
- Manpage: added manpage generation and installation.
- Nested programs: Nested programs no longer need to have END PROGRAM.
- National literals: added basic support for national literals.
- Numeric literals: added ACUCOBOL numeric literals: B#.. . for binary, O#.. . for octal, and X#.. . and H#.. . for hexadecimal.
- Literals: fixed heap corruptions caused by uncommon literals (bug #195).
- Literals: allow concatenation of literal and Boolean literals.
- Memory management: all memory belonging to the parsers and lexers is freed upon a compiler abend.
- Memory management: fixed memory leaks due to recursive CALLs.
- Microsoft Visual C++: output when compiling with cl.exe is now filtered and temporary files are deleted.
- MinGW: fixed use of wrong directory separator.
- Signals: removed error message on SIGPIPE.
- Signals: added error message for SIGBUS.
- Translations: updated, with new support for German and Italian.
- User-defined functions: function definitions must now end with END FUNCTION.
- User-defined functions: function definitions may no longer be nested in programs (bug #255).
- Windows support: allow linking with asm files.
- Windows support: added support for DISAM in the batch file which creates distributables
- Windows support: fixed environment-setting batch files not working with Microsoft Visual Studio 2017.
- Windows support: fixed 64-bit environment-setting batch files not checking the correct directories for binaries and libraries.

2. Configuration options

- Deleted compiler configuration options: eject-statement, COBOL85-reserved.
- New compiler configurations: all dialects have been split into standard and strict dialects, with strict dialects maintaining source compatibility with the dialect's compiler(s).
- New compiler configurations: acu for ACUCOBOL, COBOL2014 for COBOL 2014, rm for RM-COBOL, xopen for X/Open.
- New compiler configuration options: accept-display-extensions, accept-update, accept-auto, acu-literals, arithmetic-osys, call-overflow, console-is-crt, constant-01,

constant-78, constant-folding, define-constant-directive, hexadecimal-boolean, hexadecimal-national-literals, incorrect-conf-sec-order, intrinsic-function, listingstatements, literal-length, move-figurative-constant-to-numeric, movefigurative quote-to-numeric, move-ibm, national-literals, no-echo-means-secure. not-exceptionbefore-exception, numeric-boolean, numeric-literal-length, numericvalue-for-editeditem, pic-length, program-name-redefinition, program-prototypes, reference-out-ofdeclaratives (feature request #179), register, renames-uncommonlevels, reserved, reserved-words, stop-identifier, system-name, title-statement, use-for-debugging, word-length (feature request #43).

- Registers: compiler configurations can now specify all the registers to generate.
- Registers: added registers not yet implemented by GnuCOBOL as reserved words.
- Renamed compiler configuration options: debugging-line to debugging-mode, relaxed-syntax-checks
- Reserved words: compiler configurations can now specify all the reserved words and context-sensitive words permitted.
- Reserved words: compiler configurations can now specify whether a reserved word is an alias for another reserved word.
- Runtime configuration: added ability to configure some libcob features at runtime.
- Support options: options which specify if a feature is supported can now take a "+" before their argument to indicate it takes effect only if the current level of support is less strict than "ok".

3. Compiler directives

- \$ indicator character: added \$ as an indicator for compiler directive lines.
- >>IF directive: fixed bug #263, where nested >>IF directives were not handled correctly.
- New constants: GCCOMP, GnuCOBOL.
- New directives: >>CALL-CONVENTION, >>LISTING, >>PAGE.
- New directives (detection only): \*CBL, \*CONTROL, TITLE.
- New >>SET phrase: SOURCEFORMAT.

4. Identification division

- Comment paragraphs: fixed invalid parsing of quote characters inside comment paragraphs (bug #297).
- FUNCTION-ID: added checks for redefinition of function-names.
- INITIAL phrase: fixed premature deallocation of INITIAL programs (bug #52).
- OPTIONS paragraph: added with implementation of DEFAULT ROUNDED MODE and ENTRY-CONVENTION phrases and recognition of INTERMEDIATE ROUND-ING phrase.
- PROGRAM-ID: added checks for redefinition of program-names.
- PROGRAM-ID phrases: permit INITIAL or RECURSIVE before COMMON (bug #244).
- Program/function-names: warn if program/function-names contain spaces.

5. Environment division

- ASSIGN clause: missing ASSIGN clauses are now detected at compile-time.
- ASSIGN clause: added PRINTER and PRINTER-1 device-names for writing to a printer.

- ASSIGN clause: added CARD-PUNCH, CARD-READER, CASSETTE, INPUT, IN-PUTOUTPUT, MAGNETIC-TAPE and OUTPUT device-names for line sequential devices.
- ASSIGN clause: temporarily prohibit BASED and linkage items in ASSIGN USING due to bug #421.
- CALL-CONVENTION phrase: statically calling functions with CALL-CONVENTION 74 no longer causes linker errors (bug #316).
- CURRENCY phrase: fixed bug #182, where a preceding SWITCH phrase caused an incorrect duplicate CURRENCY clause error.
- \bullet File-control entry: fixed bug #71, where referring to a global constant caused an internal error.
- File-control entry: fixed bug #331, where using an identifier in a file record qualified with the file's name caused an error.
- FUNCTION phrase: added checks for redefinition of function-(prototype-)names.
- FUNCTION phrase: compiler will no longer stop when it encounters a syntax error.
- LOCK MODE clause: fixed combination of LOCK MODE IS AUTO-MATIC/MANUAL with LOCK ON MULTIPLE.
- PROGRAM phrase: added support for program-prototype-names.
- SIGN clause: improved syntax checks.
- SWITCH phrase: added check for duplicate on/off clauses (bug #136).
- SWITCH phrase: added new switch names: SWITCH-16 through to SWITCH-36 (feature request #65), "SWITCH 1" to "SWITCH 26" (and their aliases "SWITCH A" to "SWITCH Z"), UPSI-0 to UPSI-8 (equivalent to "SWITCH 0" to "SWITCH 8") and USW-0 to USW-31 (equivalent to "SWITCH 0" to "SWITCH 31").

6. Data division

- 78-level items: strengthened syntax checks.
- 88-level items: strengthened syntax checks.
- ANY NUMERIC clause: ANY NUMERIC items must now have PIC 9.
- ANY LENGTH clause: ANY LENGTH items may no longer be BY VALUE parameters (see bug #219).
- ANY LENGTH clause: ANY LENGTH items must now have PIC X or PIC N.
- BLANK clause: fixed bug #143, where BLANK LINE/SCREEN did not colour line/screen.
- BLANK WHEN ZERO clause: added checks that BLANK WHEN ZERO is not specified with PICTURE clauses containing S.
- Constant items: expressions in VALUE clauses now permitted.
- Data description: added a maximum record length.
- Data description: increased maximum size of non-indexed file record to 64 MiB (maximum size of an indexed file record is 65535 bytes).
- ERASE clause: fixed bug #186, where ERASE EOL and ERASE EOS could be specified simultaneously.
- FULL clause: added warning for useless FULL clauses on numeric items (feature request #209).
- HIGHLIGHT and LOWLIGHT clauses: added checks that HIGHLIGHT and LOW-LIGHT are not specified simultaneously.

- Local-storage section: fixed bug #78, where local-storage items where initialised after file section items.
- LOWLIGHT clause: implemented.
- OCCURS clause: fixed internal compiler when used with SYNC (bug #155).
- OCCURS clause: allow KEY phrase and INDEXED phrase in any order.
- OCCURS clause: fixed bug #167, where overly large numeric literals where accepted in the OCCURS clause.
- OCCURS clause (depending): require the minimum length to be less than the maximum length (feature request #99).
- OCCURS clause (depending): disabled nested OCCURS DEPENDING tables due to bugs.
- OCCURS clause (screen-section): require relative LINE/COLUMN clauses in OCCURS entries (bug #83).
- OCCURS clause (unbounded): added by Frank Swarbrick patch #50.
- PICTURE clause: restricted number of permitted PICTURE strings (bug #232).
- PICTURE clause: improved checks of constant-names referenced in PICTURE strings.
- RENAMES items: strengthened syntax checks.
- RESERVE clause: allow the optional word AREAS.
- Screen description: permit figurative constants in screen items (bug #108).
- TALLY special register: added.
- USAGE clause: added ACUCOBOL's HANDLE phrases (see feature request #77).
- VALUE clause: VALUE clauses in REDEFINES entries now cause warnings, not errors, for compatibility.
- Variable records: added checks that the minimum size of a variable record is large enough to contain the record key.

7. Procedure division

- ACCEPT statement: added ESCAPE as synonym for EXCEPTION.
- ACCEPT statement: permit clauses in any order.
- ACCEPT statement: allow WITH before every screen attribute clause.
- ACCEPT statement: entering control-C now terminates the program.
- ACCEPT statement (screen): fixed failed ACCEPTs caused by a buffer overflow.
- ACCEPT statement (screen): enhanced support for special keys (insert, tab, delete, alt-delete, etc.).
- ACCEPT statement (screen): fixed bug #161 where screens terminated after entering a few characters in a field.
- ACCEPT statement (screen): added DEFAULT as synonym for UPDATE.
- ACCEPT statement (screen): ERASE and BLANK clauses in screens are now ignored (bug #192).
- ACCEPT statement (screen): fixed bug #160 where ACCEPT statement LINE/COLUMN clauses did not work.
- ACCEPT statement (screen): fixed segfault on ACCEPT OMITTED (bug #300).
- ACCEPT statement (screen): added checks that screen attributes are not specified multiple times or after conflicting attributes.
- ACCEPT statement (screen): fixed some phrases not being recognised without being preceded by WITH (bug #402).

- ACCEPT statement (screen): fixed the backspace and delete keys not working and the insert key not toggling between insertion and overwriting.
- ACCEPT statement (screen): cursor now changes with insertion/overwrite mode (if supported by the terminal).
- ACCEPT statement (screen): a beep is emitted on attempts to insert data into a full field.
- ADD statement (corresponding): restricted to numeric items (bug #235).
- ADD statement (table): added detection of ADD TABLE.
- Addition of COMP-3 numbers: fixed bug where COMP-3 addition failed.
- Addition of floating-point numbers: fixed incorrect addition of floating-point numbers.
- CALL statement: implemented feature request #101, allowing more arguments to be provided.
- CALL statement: fixed behaviour when calling cancelled modules.
- CALL statement: added RETURNING NOTHING.
- CALL statement: the generation of C function declarations for static CALLs can now be disabled.
- CALL statement: added checks for static CALLs referring to C macros.
- CALL statement: warn if a literal containing the program-name contains spaces.
- CALL statement: added detection of NESTED phrase.
- CANCEL statement: fixed crash caused by cancelling a cancelled module.
- Conditions: restricted use of IS (bug #321).
- Conditions: added warnings for always true/false conditions (including the reason why it is always true/false).
- DESTROY statement: added detection of DESTROY.
- DISPLAY statement: permit clauses in any order.
- DISPLAY statement: allow WITH before every screen attribute clause.
- DISPLAY statement (screen): fixed bug where EC-SCREEN exceptions did not trigger ON EXCEPTION handler (bug #243).
- \bullet DISPLAY statement (screen): fixed bugs in DISPLAY SPACES/ALL X"02"/ALL X"07".
- DISPLAY statement (screen): added checks that screen attributes are not specified multiple times or after conflicting attributes.
- DISPLAY statement (screen): DISPLAY OMITTED marked as unfinished; currently equivalent to DISPLAY LOW-VALUE.
- DISPLAY statement (screen): fixed some phrases not being recognised without being preceded by WITH (bug #402).
- END DECLARATIVES phrase: fixed bug #88, where an erroneous unreachable code warning was emitted for code without a main procedure.
- ENTRY statement: suppress incorrect unreachable code warnings.
- Exception handlers: permit NOT ON EXCEPTION/END-OF-PAGE/etc. before ON EXCEPTION/END-OF-PAGE/etc.
- EXIT statement: added extension RETURNING/GIVING clause for PROGRAM phrase.
- File I-O: added detection of and handling for error when no disc space is available for output files.

- File I-O: added RETRY and ADVANCING ON LOCK as pending features.
- File I-O: fixed detection of DISAM file handler.
- FREE statement: NULL addresses no longer cause an exception.
- GOBACK statement: added extension RETURNING/GIVING clause.
- INITIALIZE statement: fixed bug #84, where literals could be passed to INITIALIZE.
- INITIALIZE statement: fixed bug #287, where reference-modified group items were not treated like elementary items.
- INSPECT statement: fixed bug #47, where clauses were permitted in invalid orders.
- LENGTH OF phrase: fixed bug #89, where the length of REDEFINES item where calculated incorrectly.
- LENGTH OF phrase: fixed bug #110, where LENGTH OF was not allowed in the UNTIL phrase of a PERFORM statement or in a VALUE clause.
- MOVE statement: added more checks for overlapping MOVE statements.
- MOVE statement: fixed truncation of COMP numbers not conforming to the binary truncate setting (bug #69).
- MOVE statement: fixed bug #344, where trying to MOVE to a procedure-name caused a segfault.
- MOVE statement: added support for IBM's character-by-character MOVE.
- PERFORM statement: fixed bug #368, where the compiler segfaulted when there was a PERFORM statement with an empty body and DEBUGGING MODE was specified.
- Procedure division header: fixed bug #55, where a user-defined function without parameters failed to compile.
- Procedure division header: disabled the BY VALUE phrase, pending a working implementation.
- Procedure division header: fixed bug #349, where BY VALUE pointer parameters lead to code that could not be compiled by older versions of Microsoft Visual C++.
- Procedure division header: RETURNING items must now be declared in the linkage section.
- Procedure division header: added RETURNING OMITTED.
- Procedure division header: added entry-convention specifiers.
- Procedure division header: now mandatory in function definitions (see bug #271).
- Procedure division header: CHAINING programs may no longer be called by other programs (bug #354), per the ACUCOBOL implementation.
- Reference modification: fixed bug #146, where the length of reference-modified item in an OCCURS DEPENDING table was too long because it was assumed the OCCURS DEPENDING table was at its maximum size.
- READ statement: a failed second READ of a missing OPTIONAL file now results in a file status of 46, not 23.
- REWRITE statement: added REWRITE FILE (feature request #170).
- Screen I-O: added detection of situations which raise EC-SCREEN-LINE-NUMBER, EC-SCREEN-STARTING-COLUMN and EC-SCREEN-ITEM-TRUNCATED.
- Screen I-O: added support for the LINE 0 and COL 0 extensions.
- Screen I-O: added some ACUCOBOL synonyms (NO ECHO, OFF, REVERSED, REVERSE, etc.).

- Screen I-O: added detection of ACUCOBOL's non-standard clauses like TAB, NOECHO, STANDARD, BACKGROUND-HIGH, BACKGROUND-LOW, BACKGROUND-STANDARD and SIZE.
- SEARCH statement (ALL): fixed bug #314, where SEARCH ALL with an empty OCCURS DEPENDING table did not exit as soon as possible.
- Segment numbers: added syntax checks.
- SET statement (address): disallowed changing address of non-01/77-level item (bug #366).
- SET statement (attribute): made HIGHLIGHT ON imply LOWLIGHT OFF and vice versa.
- SET statement (exception): added.
- SET statement (thread): added detection of ACUCOBOL extension.
- STOP statement (identifier): added (see bug #320).
- STOP statement (literal): fixed segfault.
- STOP statement (thread): added detection of ACUCOBOL extension.
- STRING statement: strengthened syntax checks (bug #259).
- SUBTRACT statement (corresponding): restricted to numeric items (bug #235).
- SUBTRACT statement (table): added detection of SUBTRACT TABLE.
- Tracing: fixed bug #216, where a segfault occurred with a program made from modules some of which had been compiled with tracing and physical CANCEL enabled and some of which had not.
- UNSTRING statement: fixed bug #54, where the POINTER value was calculated incorrectly when the delimiter was longer than one character.
- UNSTRING statement: allow a literal to be the subject of an UNSTRING.
- WRITE statement: added WRITE FILE (feature request #170).

8. Intrinsic functions

- New functions (ACUCOBOL): ABSOLUTE-VALUE (synonym for ABS).
- New functions (COBOL 2014): FORMATTED-CURRENT-DATE, FORMATTED-DATE, FORMATTED-DATETIME, FORMATTED-TIME, INTEGER-OF-FORMATTED-DATE, TESTFORMATTED-DATETIME.
- ISO-8601-date-handling functions: added extension SYSTEM-OFFSET as replacement for last optional argument.
- ISO-8601-date-handling functions: added EC-IMP-UTC-UNKNOWN if a time format ending in Z is provided but the timezone cannot be found.
- LENGTH function: added detection of PHYSICAL phrase.
- RANDOM function: fixed non-random number generation.

9. Built-in subprograms

- CBL\_GC\_FORK: added.
- CBL\_GC\_PRINTABLE: renamed from C\$PRINTABLE.
- CBL\_GC\_WAITPID: added.
- CBL\_SET\_CSR\_POS: added (feature requests #148 and #187).
- CBL\_READ\_KBD\_CHAR: added (feature requests #148 and #187).

End of Appendix F1 Summary of Compiler Changes since 2009 and version v2.2

Index

| II . | -Wobsolete Compiler Switch |
|--|--|
| " (Quote) | -x Compiler Switch 567, 582, 605, 631 |
| \$ | • |
| \$ Directives | . (Punctuation) |
| & | / |
| & (Literal Concatenation) | / (Division) |
| , | |
| ' (Apostrophe) | ; (Punctuation) |
| * | > |
| * (Multiplication) | >>CALL-CONVENTION 58 >>D 69 >>D (Debugging Line) 31 >>DEFINE 63 >>DISPLAY 70 |
| + (Addition) | >>ELIF |
| , (Punctuation) | >>SET |
| - (Character in Words/Names) | ^ |
| - (Subtraction) 39 - (Unary Sign Reversal) 38 - In Column 7 (Continuation) 32 -b Compiler Switch 605 | ^ (Exponentiation) |
| -conf Compiler Switch 574 -debug Compiler Switch 219, 382, 383, 467 -fdebugging-line Compiler Switch 81, 219 -ffold-call Compiler Switch 584 | Character in user-defined words) |
| -ffold-copy Compiler Switch66, 574-fintrinsics Compiler Switch363-fintrinsics=ALL Compiler Switch93 | 0 01-Level Constants |
| -fixed Compiler Switch 25, 66, 67 -foptional-file Compiler Switch 96 -free Compiler Switch 25, 66, 67 -fsyntax-extension Compiler Switch 91 | 6 66-Level Data Items |
| -ftrace Compiler Switch | 7 |
| -g Compiler Switch 382, 383, 467 -I Compiler Switch 574 -m Compiler Switch 567, 582, 605 -o Compiler Switch 567, 582 | 77-Level Data Items 137 78-Level Data Items 138 |
| -O Compiler Switch 601 -O2 Compiler Switch 601 | 8 88-Level Data Items |
| -Os Compiler Switch 601 | |

| \mathbf{A} | AUTHOR | |
|---------------------------------------|--------------------------------|-------------|
| A Sample Screen | AUTO 1 | |
| ABS | AUTO-SKIP 1 | |
| ACCEPT | AUTOTERMINATE | 143 |
| ACCEPT data-item | | |
| ACCEPT FROM COMMAND-LINE | В | |
| ACCEPT FROM CONSOLE | D | |
| ACCEPT FROM DATE/TIME | BACKGROUND-COLOR 1 | 144 |
| ACCEPT FROM ENVIRONMENT 233 | BASED | 145 |
| ACCEPT FROM EXCEPTION-STATUS 244 | BEEP | |
| ACCEPT FROM Runtime-Info | BEFORE ADVANCING | 361 |
| ACCEPT FROM Screen-Info | BELL | 147 |
| ACCEPT OMITTED | Binary Truncation 5 | |
| ACCESS MODE DYNAMIC 103, 106 | BIT-OF 4 | |
| ACCESS MODE RANDOM 103, 106 | BIT-TO-CHAR | |
| ACCESS MODE SEQUENTIAL 100, 101, 105 | BLANK | |
| ACOS | BLANK WHEN ZERO 1 | |
| ADD | BLINK | |
| ADD CORRESPONDING | BLOCK CONTAINS | |
| ADD GIVING 247 | BOOLEAN-OF-INTEGER | |
| ADD TO | Built-In System Subroutines 4 | |
| Additional Reference Sources | BY CONTENT 255, 609, 6 | |
| ADDRESS OF | BY REFERENCE 212, 255, 609, 6 | |
| ADVANCING PAGE | BY VALUE | |
| AFTER | BYTE-LENGTH | 369 |
| AFTER ADVANCING | | |
| AFTER EXCEPTION CONDITION | | |
| ALL | \mathbf{C} | |
| ALL INTRINSIC | C Main Programs Calling | |
| ALL OTHER 95 | GnuCOBOL Subprograms6 | 317 |
| ALLOCATE | C\$CALLEDBY | |
| Alphabet-Name-Clause | C\$CHDIR4 | |
| Alphabetic Data Item 629 | C\$COPY 4 | |
| Alphabetic Data Items | C\$DELETE4 | |
| ALPHABET 88 | C\$FILEINFO 4 | |
| ALPHABETIC292 | C\$GETPID | |
| Alphanumeric Data Item 629 | C\$JUSTIFY | 183 |
| Alphanumeric Data Items | C\$MAKEDIR4 | 184 |
| Alphanumeric Literal | C\$NARG 4 | 185 |
| Alphanumeric Literal (Hexadecimal) | C\$PARAMSIZE4 | 186 |
| Alphanumeric Literal (Zero-Delimited) | C\$PRINTABLE 4 | 187 |
| Alphanumeric Literals | C\$SLEEP | 188 |
| ALPHANUMERIC | C\$TOLOWER | 189 |
| ALPHANUMERIC-EDITED | C\$TOUPPER4 | 1 90 |
| ALSO 62, 277 | Call Environment | 589 |
| Alternate Entry Points | Called Program | 329 |
| ALTER | Called Program Considerations6 | 310 |
| ALTERNATE RECORD KEY 106 | Calling Program | 329 |
| An Example | Calling Program Considerations | 309 |
| ANNUITY | CALL | |
| ANY | CALL-CONVENTION | 85 |
| ANY LENGTH | CANCEL 2 | 257 |
| Area 'A' (Columns 8-11) | Case Insensitivity | 10 |
| Area 'B' (Columns 12-72) | CBL_AND 4 | |
| ARGUMENT-NUMBER 231, 264 | CBL_CHANGE_DIR4 | |
| ARGUMENT-VALUE | CBL_CHECK_FILE_EXIST4 | 193 |
| Arithmetic Expressions | CBL_CLOSE_FILE | |
| ASCENDING KEY | CBL_COPY_FILE 4 | 195 |
| ASCII | CBL_CREATE_DIR4 | 196 |
| ASIN | CBL_CREATE_FILE4 | |
| AT END | CBL_DELETE_DIR4 | 198 |
| AT END + NOT AT END | CBL_DELETE_FILE4 | |
| ATAN | CBL_EQ | 500 |

| CBL_ERROR_PROC | COB_SORT_MEMORY Environment Variable 34 |
|---|---|
| CBL_EXIT_PROC | COB_SWITCH_n |
| CBL_FLUSH_FILE | COB_SWITCH_n Environment Variable 9 |
| CBL_GC_FORK | COB_SYNC |
| CBL_GC_GETOPT | COB_TRACE_FILE |
| CBL_GC_HOSTED | cobc - The GnuCOBOL Compiler |
| CBL_GC_NANOSLEEP | cobc option -Xref an example 568 |
| CBL_GC_PRINTABLE | COBCPY |
| CBL_GC_WAITPID515 | COBCPY Environment Variable |
| CBL_GET_CSR_POS | cobcrun - Command-line Execution 585 |
| CBL_GET_CURRENT_DIR517 | COBOL Fundamentals |
| CBL_GET_SCR_SIZE | CODE-SET |
| CBL_IMP | Collating Sequence |
| CBL_NIMP | COLLATING SEQUENCE 82, 95, 303 |
| CBL_NOR | Color Palette |
| CBL_NOT 522 | Color Palette and Video Attributes |
| CBL_OPEN_FILE | Column 7 (Indicator Area) |
| CBL_OR | Columns 1-6 (Sequence Number Area) |
| CBL_READ_FILE | Columns 12-72 (Area B) |
| CBL_READ_KBD_CHAR | Columns 73-80 (Program Name Area) 20 |
| CBL_RENAME_FILE | Columns 8-11 (Area A) |
| CBL_SET_CSR_POS | COLUMN |
| CBL_TOLOWER | COLUMNS |
| CBL_TOUPPER | Combined Conditions4 |
| CBL_WRITE_FILE | COMBINED-DATETIME |
| CBL_XOR | Combining GnuCOBOL and C Programs 614 |
| CDF - Compiler Directing Facility 57 | COMMAND-LINE |
| CHAR 370 | Comments |
| CHAR-NATIONAL | COMMIT |
| Class Conditions | Common Clauses on Executable Statements 220 |
| Class-Definition-Clause | COMMON |
| CLASSIFICATION82 | Compilation Group |
| CLOSE | Compilation Time Environment Variables 57 |
| COB-CRT-STATUS | Compilation Unit |
| COB_CC | Compiler Configuration Files |
| COB_CFLAGS | Compiler Switches, -b 609 |
| COB_CONFIG_DIR | Compiler Switches, -conf 574 |
| COB_CONFIG_DIR Environment Variable 575 | Compiler Switches, -debug 219, 382, 383, 467 |
| COB_COPY_DIR | Compiler Switches, -fdebugging-line 81, 219 |
| COB_DISPLAY_WARNINGS | Compiler Switches, -ffold-call |
| COB_LDADD | Compiler Switches, -ffold-copy 66, 574 |
| COB_LDFLAGS | Compiler Switches, -fintrinsics |
| COB_LIBRARY_PATH | Compiler Switches, -fintrinsics=ALL |
| COB_LIBRARY_PATH | Compiler Switches, -fixed |
| Environment Variable | Compiler Switches, -foptional-file |
| COB_LIBS | Compiler Switches, -free |
| COB_LOAD_CASE | Compiler Switches, -fsyntax-extension |
| COB_LOAD_CASE Environment Variable 606 | Compiler Switches, -ftrace 320, 322, 584 |
| COB_PHYSICAL_CANCEL584 | Compiler Switches, -ftraceall 322, 382, 383, 467, 58- |
| COB_PHYSICAL_CANCEL | Compiler Switches, -g |
| Environment Variable | Compiler Switches, -I |
| COB_PRE_LOAD | Compiler Switches, -m |
| COB_PRE_LOAD Environment Variable 255, 606 | Compiler Switches, -o |
| COB_SCREEN_ESC 585 | Compiler Switches, -O |
| COB_SCREEN_ESC Environment Variable 236 | Compiler Switches, -O2 |
| COB_SCREEN_EXCEPTIONS585 | Compiler Switches, -Os |
| COB_SCREEN_EXCEPTIONS | Compiler Switches, -Wobsolete |
| Environment Variable | Compiler Switches, -x |
| COB_SET_DEBUG | Compiling Programs |
| COB_SET_DEBUG Environment Variable 219 | COMPUTE 260 |
| COB_SET_TRACE | COMPUTE Versus |
| COB_SET_TRACE Environment Variable 320, 322 | ADD-SUBTRACT-MULTIPLY-DIVIDE 620 |
| COB_SORT_MEMORY | CONCATENATE |

| Concurrent Access to Files | DELIMITED BY | 356 |
|---|--|-----|
| Condition Names | DELIMITER | |
| Conditional Expressions | DEPENDING ON | |
| CONFIGURATION SECTION | DESCENDING KEY | |
| CONSOLE | Detail Group | |
| CONSOLE IS CRT | detail report | |
| CONSTANT 63, 66, 116, 153 | Detail Report | |
| Contained Subprograms | Direct Execution | |
| CONTENT | DISPLAY | |
| Continuation (- in Column 7) | DISPLAY data-item | |
| CONTINUE | DISPLAY Data-Item | |
| Control Break | DISPLAY UPON COMMAND-LINE | |
| Control Field | DISPLAY UPON device | |
| Control Footing | DISPLAY UPON ENVIRONMENT-NAME | |
| Control Heading | DISPLAY-OF | |
| Control Hierarchy | DIVIDE | |
| Control Hierarchy (Revisited) | DIVIDE BY GIVING | |
| CONTROL | DIVIDE INTO | |
| CONVERSION | DIVIDE INTO GIVING | |
| CONVERTING | Division | |
| Copybook | Divisions | |
| Copybook Naming Conventions and Usage 625 | Divisions Organize Programs | |
| Copybooks | DUPLICATES | |
| COPY | Dynamic Subprogram | |
| CORRESPONDING | Dynamic vs Static Subprograms | |
| COS | Dynamically Loaded Subprograms | |
| COUNT 357 | Dynamically Dedded Suspregrams | 000 |
| Cross Reference listing using cobxref | | |
| CRT STATUS85 | \mathbf{E} | |
| CRT STATUS Codes | | 00/ |
| CURRENCY SIGN | E | |
| CURRENCY-SYMBOL 374 | Elementary Item | |
| current character pointer | ELSE | |
| CURRENT-DATE 375 | EMPTY-CHECK | |
| CURSOR IS | | |
| 0 0 1 0 0 1 0 1 0 1 0 1 0 1 0 1 0 0 0 0 | Entry-point | |
| | Entry-point Name | |
| D | ENTRY Environment Variables, COB_CONFIG_DIR | |
| D In Column 7 (Debugging Line) | Environment Variables, COB_CONFIG_DIR | 376 |
| Data | COB_LIBRARY_PATH 583, | 606 |
| Data Definition Principles | Environment Variables, COB_LOAD_CASE | |
| Data Description Clauses | Environment Variables, COB_LOAD_CASE | 000 |
| Data Initialization 23 | COB_PHYSICAL_CANCEL | 606 |
| Data Item | Environment Variables, COB_PRE_LOAD 255, | |
| Data Item Coding and Naming Conventions 622 | Environment Variables, COB_SCREEN_ESC | |
| DATA DIVISION | Environment Variables, | 200 |
| DATA RECORD | COB_SCREEN_EXCEPTIONS | 236 |
| DATE-COMPILED | Environment Variables, COB_SET_DEBUG | |
| DATE-MODIFIED | Environment Variables, | 21, |
| DATE-OF-INTEGER 376 | COB_SET_TRACE | 329 |
| DATE-TO-YYYYMMDD | Environment Variables, | 022 |
| DATE-WRITTEN | COB_SORT_MEMORY | 340 |
| DAY-OF-INTEGER | Environment Variables, COB_SWITCH_n | |
| DAY-TO-YYYYDDD | Environment Variables, COBCPY | |
| DB_HOME | Environment Variables, DB_HOME | |
| DB_HOME Environment Variable | Environment Variables, LANG 374, 423, 424, 4 | |
| DEBUG-ITEM Special Register | | 420 |
| DEBUGGING MODE | Environment Variables, LD_LIBRARY_PATH | |
| DECIMAL POINT IS COMMA | Environment Variables, PATH | |
| DECLARATIVES | Environment Variables, TEMP | |
| DEFAULT | Environment Variables, TMP | |
| DEFINED | Environment Variables, TMPDIR | |
| DELETE | Environment Variables: Compilation-Time | |

| Environment Variables: Run-Time 584 | FRACTION-PART |
|---|--|
| ENVIRONMENT | Free Format Mode |
| ENVIRONMENT DIVISION | FREE |
| ENVIRONMENT-NAME | FROM |
| ENVIRONMENT-VALUE | FROM CRT 234 |
| EOL 155 | FULL |
| EOS 155 | FUNCTION93 |
| ERASE | FUNCTION-ID |
| Error Exception Codes | Functions |
| Error Type Strings | |
| ERROR | G |
| ESCAPE KEY | |
| EVALUATE | General Environment |
| EVENT STATUS | General instructions |
| EXCEPTION STATUS | Generated Report Pages |
| EXCEPTION-FILE | GENERATE 286 |
| EXCEPTION-FILE-N | GIVING |
| EXCEPTION-LOCATION | GLOBAL |
| EXCEPTION-LOCATION-N | GLOBAL Data Items |
| | Glossary of Terms |
| EXCEPTION-STATUS | GnuCOBOL Main Programs |
| Executing Dynamically-Loadable Libraries | CALLing C Subprograms |
| Executing Dynamicany-Loadable Libraries | GnuCOBOL Run-Time Library Requirements 614 |
| EXHIBIT | GnuCOBOL Statements |
| EXIT | GO TO |
| EXP | GO TO DEPENDING ON 289 |
| EXP10 | GOBACK |
| EXTEND | Group Item |
| EXTERNAL | GROUP INDICATE |
| EXTERNAL Data Items 611 | Grouped Word Lists by feature and function 639 |
| | • |
| To | TT |
| H | П |
| FACTORIAL | H HEADING 198 |
| FACTORIAL | HEADING |
| FACTORIAL | HEADING 125
HEX-OF 474 |
| FACTORIAL | HEADING 125 HEX-OF 474 HEX-TO-CHAR 478 |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 | HEADING 125 HEX-OF 474 HEX-TO-CHAR 475 Hexadecimal Alphanumeric Literal 32, 631 |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables | HEADING 125 HEX-OF 474 HEX-TO-CHAR 475 Hexadecimal Alphanumeric Literal 32, 631 Hexadecimal Numeric Literal 31, 632 |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 | HEADING 125 HEX-OF 474 HEX-TO-CHAR 475 Hexadecimal Alphanumeric Literal 32, 631 Hexadecimal Numeric Literal 31, 632 HIGHEST-ALGEBRAIC 394 |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 | HEADING 125 HEX-OF 474 HEX-TO-CHAR 475 Hexadecimal Alphanumeric Literal 32, 631 Hexadecimal Numeric Literal 31, 632 HIGHEST-ALGEBRAIC 394 HIGHLIGHT 163 |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables 597 File OPEN Modes 309 File Sharing 52 | HEADING 125 HEX-OF 474 HEX-TO-CHAR 475 Hexadecimal Alphanumeric Literal 32, 631 Hexadecimal Numeric Literal 31, 632 HIGHEST-ALGEBRAIC 394 |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 | HEADING 125 HEX-OF 474 HEX-TO-CHAR 475 Hexadecimal Alphanumeric Literal 32, 631 Hexadecimal Numeric Literal 31, 632 HIGHEST-ALGEBRAIC 394 HIGHLIGHT 163 How RWCS Builds Report Pages 539 |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 | HEADING 125 HEX-OF 474 HEX-TO-CHAR 475 Hexadecimal Alphanumeric Literal 32, 631 Hexadecimal Numeric Literal 31, 632 HIGHEST-ALGEBRAIC 394 HIGHLIGHT 163 |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 | HEADING 125 HEX-OF 474 HEX-TO-CHAR 475 Hexadecimal Alphanumeric Literal 32, 631 Hexadecimal Numeric Literal 31, 632 HIGHEST-ALGEBRAIC 394 HIGHLIGHT 163 How RWCS Builds Report Pages 539 |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 FILLER 111 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables 590 File JOEN Modes 309 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 FILLER 111 FINAL 126 FIRST DETAIL 125 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables 590 File OPEN Modes 309 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 FILLER 111 FINAL 126 FIRST DETAIL 125 Fixed Format Mode 25, 67, 631 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 FILLER 111 FINAL 126 FIRST DETAIL 125 Fixed Format Mode 25, 67, 631 FOLDCOPYNAME 66 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 FILLER 111 FINAL 126 FIRST DETAIL 125 Fixed Format Mode 25, 67, 631 FOLDCOPYNAME 66 FOOTING 125 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 FILLER 111 FINAL 126 FIRST DETAIL 125 Fixed Format Mode 25, 67, 631 FOLDCOPYNAME 66 FOOTING 125 FOOTING 125 FOOTING AT 114 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 FILLER 111 FINAL 126 FIRST DETAIL 125 Fixed Format Mode 25, 67, 631 FOLDCOPYNAME 66 FOOTING 125 FOOTING AT 114 FOREGROUND-COLOR 158 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 FILLER 111 FINAL 126 FIRST DETAIL 125 Fixed Format Mode 25, 67, 631 FOLDCOPYNAME 66 FOOTING 125 FOOTING AT 114 FOREGROUND-COLOR 158 FOREVER 311 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 FILLER 111 FINAL 126 FIRST DETAIL 125 Fixed Format Mode 25, 67, 631 FOLDCOPYNAME 66 FOOTING 125 FOOTING AT 114 FOREGROUND-COLOR 158 FOREVER 311 Format of Program Source Lines 25 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 FILLER 111 FINAL 126 FIRST DETAIL 125 Fixed Format Mode 25, 67, 631 FOLDCOPYNAME 66 FOOTING 125 FOOTING AT 114 FOREGROUND-COLOR 158 FOREVER 311 Format of Program Source Lines 25 FORMATTED-CURRENT-DATE 389 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 FILLER 111 FINAL 126 FIRST DETAIL 125 Fixed Format Mode 25, 67, 631 FOLDCOPYNAME 66 FOOTING 125 FOOTING 125 FOOTING AT 114 FOREGROUND-COLOR 158 FOREVER 311 Format of Program Source Lines 25 FORMATTED-CURRENT-DATE 389 FORMATTED-CURRENT-DATE 389 | HEADING |
| FACTORIAL 388 FALSE 157 Figurative Constants 32, 631 File I/O 590 File I/O Environment Variables and/or dictionary file 597 File OPEN Modes 309 File Sharing 52 File Status Codes 98 File-Based SORT 339 File/Sort-Description 113 FILE SECTION 112 FILE STATUS 98 FILE-SECTION-Data-Item 116 Files 13 FILLER 111 FINAL 126 FIRST DETAIL 125 Fixed Format Mode 25, 67, 631 FOLDCOPYNAME 66 FOOTING 125 FOOTING AT 114 FOREGROUND-COLOR 158 FOREVER 311 Format of Program Source Lines 25 FORMATTED-CURRENT-DATE 389 | HEADING |

| INPUT-OUTPUT SECTION 94 | LOCALE-TIME-FROM-SECONDS | |
|---|------------------------------|------|
| INSPECT | Locating Copybooks | |
| INSTALLATION | LOCK99, | |
| INTEGER 395 | LOCK ON | . 54 |
| INTEGER-OF-BOOLEAN | LOG | 406 |
| INTEGER-OF-DATE | LOG10 | 407 |
| INTEGER-OF-DAY | LOWER | . 66 |
| INTEGER-OF-FORMATTED-DATE398 | LOWER-CASE | |
| INTEGER-PART | LOWEST-ALGEBRAIC | |
| Interfacing to Other Environments | LOWLIGHT | |
| Interfacing With The OS | LOW LIGHT | 10. |
| INTO | | |
| Intrinsic Function | ${f M}$ | |
| Intrinsic Functions | | |
| | Main Program | |
| INTRINSIC | Main program | 632 |
| Introducing COBOL | Marking Changes in Programs | 621 |
| Introduction3 | Matching C Data Types with | |
| INVALID KEY + NOT INVALID KEY 222 | GnuCOBOL USAGE's | 615 |
| | MAX | 410 |
| т | MEAN | 411 |
| J | MEDIAN | |
| JUSTIFIED | MEMORY SIZE | |
| | MERGE | |
| | MIDRANGE | |
| K | MIN | |
| KEY | MOD | |
| KE1 175, 505, 519 | MODE IS BLOCK | |
| | | |
| ${f L}$ | MODULE-CALLER-ID | |
| | MODULE-DATE | |
| LABEL RECORD 113 | MODULE-FORMATTED-DATE | |
| LANG Environment Variable 374, 423, 424, 425, 426 | MODULE-ID | |
| Language Reserved Words | MODULE-PATH | |
| LAST CONTROL125 | MODULE-SOURCE | |
| LAST DETAIL | MODULE-TIME | |
| LD_LIBRARY_PATH | MONETARY-DECIMAL-POINT | |
| LD_LIBRARY_PATH Environment Variable 567 | MONETARY-THOUSANDS-SEPARATOR | 424 |
| LEADING | MOVE | |
| LEFTLINE | MOVE CORRESPONDING | 306 |
| LENGTH | multiple record locking | . 54 |
| LENGTH-AN | MULTIPLE FILE | |
| LENGTH-CHECK | MULTIPLY | |
| Level Number | MULTIPLY BY | |
| | MULTIPLY GIVING | |
| LINAGE IS n LINES | MODIN DI GIVING | 000 |
| LINAGE-COUNTER Special Register 114, 361 | | |
| LINE | $\mathbf N$ | |
| LINE ADVANCING | | |
| LINE-COUNTER | National Character set | |
| LINE-COUNTER Special Register 126, 296, 352, 540 | NATIONAL | |
| LINES | NATIONAL-EDITED | |
| LINES AT BOTTOM 114 | NATIONAL-OF | 469 |
| LINES AT TOP | NATIVE | |
| LINKAGE SECTION | Negated Conditions | . 48 |
| Literal | Nested Subprograms | 604 |
| Literal Concatenation (&) | NEXT170, | |
| Literals | NEXT GROUP | |
| Literals (Alphanumeric) | NEXT PAGE | |
| Literals (Numeric) | NEXT SENTENCE | |
| LOCAL-STORAGE SECTION | NO ADVANCING | |
| LOCALE | NO REWIND | |
| LOCALE Names | NO REWIND 258, | |
| | NOFOLDCOPYNAME | |
| LOCALE DATE 402 | | |
| LOCALE TIME 403 | NORMAL | |
| LOCALE-TIME | NOT | . 48 |

| NOT INVALID KEY | perform scope | |
|---|-----------------------------------|----|
| NOT ON EXCEPTION | PERFORM 31 | |
| NOT ON OVERFLOW 223 | PI | |
| NOT ON SIZE ERROR 224 | PICTURE | |
| Null Terminated Literals | POINTER 34 | |
| Numeric Data Item | Predefined compilation variables | |
| Numeric Data Items | Predefined Compilation Variables | |
| Numeric Edited | PRESENT WHEN 18 | |
| Numeric Edited Data Item 633 | PRESENT-VALUE 43 | |
| Numeric Literal | PREVIOUS | |
| Numeric Literal (Hexadecimal) | Primary Entry-Point | |
| Numeric Literals | PRINTER | |
| NUMERIC | PRINTING | 59 |
| NUMERIC SIGN TRAILING SEPARATE 86 | Procedural PERFORM | 11 |
| NUMERIC-DECIMAL-POINT | Procedure | 33 |
| NUMERIC-EDITED | Procedure name | 33 |
| NUMERIC-THOUSANDS-SEPARATOR 426 | Procedure Names | 17 |
| NUMVAL | PROCEDURE DIVISION 21 | 11 |
| NUMVAL-C | PROCEDURE DIVISION CHAINING 21 | 14 |
| NUMVAL-C-V2 | PROCEDURE DIVISION RETURNING 21 | |
| NUMVAL-F | PROCEDURE DIVISION Sections | |
| | and Paragraphs | 17 |
| | PROCEDURE DIVISION Sections | |
| O | Versus Paragraphs | 25 |
| OBJECT-COMPUTER 82 | PROCEDURE DIVISION USING | 12 |
| OCCURS | Procedures | |
| OFF | Program | |
| OFF STATUS | Program Arguments | |
| OMITTED | Program Name Area (Columns 73-80) | |
| ON EXCEPTION + NOT ON EXCEPTION 223 | Program Structure | |
| | PROGRAM-ID. | |
| ON OVERFLOW + NOT ON OVERFLOW 223 | Programmer Productivity | |
| ON SIZE ERROR + NOT ON SIZE ERROR 223 | Programming Style Suggestions | |
| ON STATUS | PROMPT | |
| OPEN | PROTECTED | |
| OPTIONAL 96, 213 | Punctuation | |
| ORD | i difettation | 90 |
| ORD-MAX | | |
| ORD-MIN | Q | |
| ORGANISATION INDEXED | • | 96 |
| ORGANISATION LINE SEQUENTIAL | Qualification | |
| ORGANISATION RELATIVE | Qualification of Data Names | 3C |
| ORGANISATION SEQUENTIAL 14 | | |
| ORGANIZATION INDEXED 105 | \mathbf{R} | |
| ORGANIZATION LINE SEQUENTIAL 101 | \mathbf{n} | |
| ORGANIZATION RELATIVE | Random READ | 18 |
| ORGANIZATION SEQUENTIAL 100 | RANDOM | 36 |
| OUTPUT | RANGE 43 | 38 |
| OUTPUT PROCEDURE | Readability of Programs | 10 |
| overflow condition | READ 31 | |
| OVERLINE | READY TRACE | 20 |
| OVERRIDE | Record | |
| | Record Locking | 54 |
| D | RECORD CONTAINS 11 | |
| P | RECORD DELIMITER | |
| Page Footing | RECORD IS VARYING | |
| Page Heading | RECORD KEY 106, 26 | |
| PAGE | RECORDING MODE | |
| PAGE LIMITS | Recursive Subprogram | |
| PAGE-COUNTER | Recursive Subprograms 61 | |
| PAGE-COUNTER Special Register 126, 296, 352 | RECURSIVE | |
| PARAMETER | REDEFINES | |
| PATH | REEL 25 | |
| PATH Environment Variable | Reference Modifiers | |
| | | • |

| REFERENCE | SELECT |
|---|--|
| Relation Conditions | Sentence |
| RELATIVE KEY | SEPARATE CHARACTER |
| RELEASE | Sequence Number Area (Columns 1-6) |
| REM | Sequential READ |
| REMAINDER | SET |
| REMARKS | SET ADDRESS |
| RENAMES | SET ATTRIBUTE |
| REPLACE | SET Condition Name |
| REPLACING 60, 61, 293, 297 | SET ENVIRONMENT |
| Report Footing | SET Index |
| Report Group | SET LAST EXCEPTION |
| Report Group Definitions | SET Program-Pointer |
| Report Heading | SET Switch |
| Report I/O | SET UP/DOWN |
| Report Writer Features | Sharing Data Between Calling and |
| Report Writer Usage | Called Programs 609 |
| REPORT IS | SHARING |
| REPORT SECTION | Sign Conditions |
| REPORT SECTION Data Items | SIGN |
| REPOSITORY | SIGN IS |
| REQUIRED | Simple GO TO |
| Reserved Word | Simple MOVE |
| Reserved Word Lists | single record locking |
| Reserved Words | SIN |
| RESERVE | So What is GnuCOBOL? |
| RESET | Sorting and Merging Data |
| RETURN | SORT |
| RETURN-CODE Special Register 254, 345, 476, 477, | SORT STATUS |
| 478, 479, 480, 481, 482, 484, 486, 491, 492, 493, 494, | Source Line Format, Fixed |
| 476, 479, 460, 461, 462, 464, 460, 491, 492, 493, 494, 495, 496, 497, 498, 499, 500, 501, 503, 517, 519, 520, | Source Line Format, Free |
| 521, 522, 523, 524, 525, 527, 530, 531, 603, 607, 608 | SOURCE |
| RETURNING | SOURCE IS |
| REVERSE | |
| REVERSE-VIDEO | Sparse Keys |
| REVERSED | Special Registers |
| REWRITE | Special Registers, DEBUG-ITEM |
| ROLLBACK | Special Registers, LINAGE-COUNTER 114, 36: |
| ROUNDED | Special Registers, LINE-COUNTER 126, 296, 352 |
| Run Time Environment Variables | 54 |
| Running Programs | Special Registers, PAGE-COUNTER 126, 296, 355 |
| RUN | Special Registers, RETURN-CODE 254, 345, 476 |
| RWCS Lexicon | 477, 478, 479, 480, 481, 482, 484, 486, 491, 492, 493 |
| | 494, 495, 496, 497, 498, 499, 500, 501, 503, 517, 519 |
| | 520, 521, 522, 523, 524, 525, 527, 530, 531, 603, 607, 608 |
| \mathbf{S} | SPECIAL-NAMES |
| SAME RECORD AREA | Split Keys |
| SAME SORT | SQRT |
| SAME SORT-MERGE | STANDARD-1 88 |
| Screen Formatting Features | STANDARD-2 |
| Screen I/O | STANDARD-COMPARE470 |
| SCREEN CONTROL | STANDARD-DEVIATION 440 |
| SCREEN SECTION | START 34 |
| SCROLL | Statement |
| Search Index | Static Subprogram |
| SEARCH | STATIC |
| SEARCH ALL | STATUS |
| SECONDS-FROM-FORMATTED-TIME | STDCALL |
| SECONDS-PAST-MIDNIGHT 442 | STDERR 8' |
| SECURE | STDIN 80 |
| SECURITY 77 | STDOUT 8' |
| SEGMENT-LIMIT | STEP |

| STOP | TEST-DATE-YYYYMMDD452 |
|---|---|
| STORED-CHAR-LENGTH 447 | TEST-DAY-YYYYDDD453 |
| String Allocation Differences Between | TEST-FORMATTED-DATETIME 454 |
| GnuCOBOL and C | TEST-NUMVAL |
| String Manipulation | TEST-NUMVAL-C |
| STRING | TEST-NUMVAL-F |
| Structured Data | The Anatomy of a Report |
| Sub-Programming | The Anatomy of a Report Page 538 |
| Subprogram | The COBOL Language - Advanced Techniques 35 |
| Subprogram Arguments 609 | The COBOL Language - The Basics |
| Subprogram Execution Flow | THRU |
| Subprogram Types | TIMEOUT |
| Subroutine | TIMES |
| Subroutine 605, 634 Subroutine Execution Flow 606 | |
| | TMP |
| Subscripting | TMP Environment Variable |
| SUBSTITUTE | TMPDIR |
| SUBSTITUTE-CASE | TMPDIR Environment Variable |
| SUBTRACT | TO |
| SUBTRACT CORRESPONDING | TRAILING 60, 62, 190, 458 |
| SUBTRACT FROM | TRANSFORM |
| SUBTRACT GIVING | TRIM |
| SUM OF | Turning PHYSICAL Page Formatting Into |
| Summary of Compiler Changes after | LOGICAL Formatting 556 |
| GnuCOBOL Compiler v2.2 | TYPE 196 |
| Summary of Compiler Changes for COBOL | |
| Compiler v4 early dev | |
| Summary of Compiler Changes for v3.1.1-Dev 679 | \mathbf{U} |
| Summary of Compiler Changes since | INDEDITATE 100 |
| 2009 and version v1-1 | UNDERLINE |
| Summary of Document Changes 673 | UNLOCK |
| summary report | UNSIGNED |
| Summary Report | UNSTRING356 |
| SUM | UNTIL |
| SUPPRESS | UNTIL EXIT 31 |
| SUPPRESS WHEN 106 | UPDATE |
| Switch-Definition-Clause | UPON |
| Switch-Status Conditions | UPON CRT |
| SWITCH-n | UPON CRT-UNDER |
| | UPPER |
| SWn 91 Symbolic-Characters-Clause 92 | UPPER-CASE |
| | USAGE |
| SYNCRONIZED | Use of Periods |
| Syntax Diagram Conventions | Use of VERB/END-VERB Constructs 50 |
| SYSERR | USE AFTER STANDARD ERROR |
| SYSIN | PROCEDURE |
| SYSIPT | USE BEFORE REPORTING |
| SYSLIST | USE FOR DEBUGGING |
| SYSLST 87 | User-Defined Function 603, 634 |
| SYSOUT 87 | User-Defined Function Execution Flow |
| System names | |
| System routines | User-Defined Names |
| SYSTEM 532 | User-Defined Words |
| | USER NAME |
| \mathbf{T} | USING |
| | |
| Table Handling | \mathbf{V} |
| Table References | • |
| Table SORT | VALUE |
| Table Subscripting versus Table Indexing 623 | VALUE OF 113 |
| TALLYING | VARIANCE |
| TAN | VARYING |
| TEMP | Verb |
| TEMP Environment Variable | , |
| TERMINATE | |

| \mathbf{W} | ${f X}$ |
|------------------------------|--|
| | X"91"533 |
| WHEN | X"E4"534 |
| WHEN OTHER | X"E5"534 |
| WHEN-COMPILED | X"F4" |
| Why YOU Should Learn COBOL 4 | X"F5" |
| WITH FILLER | V |
| WITH IGNORE LOCK 55 | Y |
| WITH LOCK 310 | YEAR-TO-YYYY |
| WITH TEST 312 | |
| WORKING-STORAGE SECTION | ${f Z}$ |
| WRITE | Zero-Delimited Alphanumeric Literals 32, 635 |